
Command Reference: SplitTableRowIntoSequence()


Split a table row into a sequence of rows

/ersion 11.00.00, 2015-01-11


The SplitTableRowIntoSequence() command uses information from a table row to create a sequence of new table rows. The new rows are inserted after the original row, which optionally can be deleted from the table after processing. The following approaches are implemented:

• Use a distance measure start and end value in the row to create segmented row distances. For example, this can be used to break a streamflow reach into segments of equal length, for example "stream mile" segments as shown in the following example. The first table illustrates input and the second the table after modification (original rows are deleted). The start and end columns can be specified in any order but the output is always with the smaller value as the start.





The following dialog is used to edit the command and illustrates the syntax of the command:



SplitTableRowIntoSequence() Command Editor

SplitTableRowIntoSequence

The command syntax is as follows:

SplitTableRowIntoSequence(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
TableID	The identifier for the table.	None – must
		be specified.
MeasureStartColumn	The name of the table column for the starting measure.	None – must
		be specified.
MeasureEndColumn	The name of the table column for the ending measure.	None – must
		be specified.
MeasureIncrement	The measure increment used to split the original distance	None – must
	into segments (e.g., .1).	be specified.
MinimumStartSegment	The minimum length of the starting segment to include.	Include start
Length		segment.
MinimumEndSegment	The minimum length of the ending segment to include.	Include end
Length		segment.
DeleteOriginalRow	Indicate whether the original table row should be deleted	False
	as False or True. Specify True if the generated	
	sequence of rows should replace the original row.	