

Enterprise Transport API

Java Edition

3.7.3.L1

VALUE ADDED COMPONENTS

Document Version: 3.7.3
Date of issue: December 2023
Document ID: ET AJ373UMVAC.230



© Refinitiv 2015 - 2023. All rights reserved.

Republication or redistribution of Refinitiv content, including by framing or similar means, is prohibited without the prior written consent of Refinitiv. 'Refinitiv' and the Refinitiv logo are registered trademarks and trademarks of Refinitiv.

Any software, including but not limited to: the code, screen, structure, sequence, and organization thereof, and its documentation are protected by national copyright laws and international treaty provisions. This manual is subject to U.S. and other national export regulations.

Refinitiv, by publishing this document, does not guarantee that any information contained herein is and will remain accurate or that use of the information will ensure correct and faultless operation of the relevant service or equipment. Refinitiv, its agents, and its employees, shall not be held liable to or through any user for any loss or damage whatsoever resulting from reliance on the information contained herein.

Contents

1	Introduction	1
1.1	About this Manual	1
1.2	Audience	1
1.3	Programming Language.....	1
1.4	Acronyms and Abbreviations	1
1.5	Additional References and Resources	3
1.6	Documentation Feedback	3
1.7	Document Conventions	3
1.7.1	<i>Optional, Conditional, and Required</i>	3
1.7.2	<i>Typographic</i>	3
1.7.3	<i>Document Structure</i>	4
1.7.4	<i>Diagrams</i>	4
2	Product Description and Overview	5
2.1	What is the Enterprise Transport API?.....	5
2.2	What are Enterprise Transport API Value Added Components?.....	6
2.3	Transport API Reactor	7
2.4	OMM Consumer Watchlist	7
2.4.1	<i>Data Stream Aggregation and Recovery</i>	7
2.4.2	<i>Additional Features</i>	7
2.4.3	<i>Usage Notes</i>	8
2.5	Administration Domain Model Representations	8
2.6	Value Added Utilities	8
2.7	Payload Cache.....	8
3	Building an OMM Consumer	9
3.1	Overview	9
3.2	Leverage Existing or Create New Reactor.....	9
3.3	Implement Callbacks and Populate Role	10
3.4	Establish Connection using Reactor.connect.....	10
3.5	Issue Requests and/or Post Information	10
3.6	Log Out and Shut Down.....	11
3.7	Additional Consumer Details.....	11
4	Building an OMM Interactive Provider	12
4.1	Overview	12
4.2	Leverage Existing or Create New Reactor.....	12
4.3	Create a Server.....	12
4.4	Implement Callbacks and Populate Role	13
4.5	Associate Incoming Connections Using Reactor.accept.....	13
4.6	Perform Login Process.....	13
4.7	Provide Source Directory Information	14
4.8	Provide or Download Necessary Dictionaries	14
4.9	Handle Requests and Post Messages	15
4.10	Dispatch Round Trip Time Messages	15
4.11	Disconnect Consumers and Shut Down	15
4.12	Additional Interactive Provider Details	16
5	Building an OMM Non-Interactive Provider	17
5.1	Building an OMM Non-Interactive Provider Overview	17

5.2	Leverage Existing or Create New Reactor	17
5.3	Implement Callbacks and Populate Role	18
5.4	Establish Connection using Reactor.connect.....	18
5.5	Download the Dictionary	18
5.6	Provide Content	19
5.7	Log Out and Shut Down	19
5.8	Additional Non-Interactive Provider Details.....	19
6	Reactor Detailed View.....	20
6.1	Concepts	20
6.1.1	<i>Functionality: Enterprise Transport API Versus Enterprise Transport API Reactor.....</i>	21
6.1.2	<i>Reactor Error Handling.....</i>	21
6.1.3	<i>Reactor Error Info Codes.....</i>	22
6.1.4	<i>Enterprise Transport API Reactor Application Lifecycle.....</i>	23
6.2	Reactor Use	23
6.2.1	<i>Creating a Reactor.....</i>	24
6.2.2	<i>Destroying a Reactor.....</i>	26
6.3	Reactor Channel Use	27
6.3.1	<i>Reactor Channel Roles.....</i>	28
6.3.2	<i>Reactor Channel Role: OMM Consumer.....</i>	30
6.3.3	<i>Reactor Channel Role: OMM Provider.....</i>	32
6.3.4	<i>Reactor Channel Role: OMM Non-Interactive Provider.....</i>	33
6.4	Managing Reactor Channels.....	34
6.4.1	<i>Adding Reactor Channels.....</i>	34
6.4.2	<i>Removing Reactor Channels.....</i>	39
6.5	Reporting on Channel Statistics.....	40
6.6	Dispatching Data	40
6.6.1	<i>Reactor Dispatch Methods</i>	40
6.6.2	<i>Reactor Callback Methods.....</i>	42
6.6.3	<i>Reactor Callback: Channel Event.....</i>	42
6.6.4	<i>Reactor Callback: Default Message</i>	45
6.6.5	<i>Reactor Callback: RDM Login Message.....</i>	46
6.6.6	<i>Reactor Callback: RDM Directory Message</i>	47
6.6.7	<i>Reactor Callback: RDM Dictionary Message.....</i>	50
6.7	Writing Data	51
6.7.1	<i>Writing Data using ReactorChannel.submit(Msg...)</i>	51
6.7.2	<i>Writing Data Using ReactorChannel.submit(TransportBuffer...)</i>	55
6.8	Creating and Using Tunnel Streams	62
6.8.1	<i>Authenticating a Tunnel Stream</i>	62
6.8.2	<i>Opening a Tunnel Stream.....</i>	63
6.8.3	<i>Negotiating Stream Behaviors: Class of Service</i>	65
6.8.4	<i>Tunnel Stream Callback Methods and Event Types.....</i>	68
6.8.5	<i>Code Sample: Opening and Managing a Tunnel Stream</i>	70
6.8.6	<i>Accepting Tunnel Streams.....</i>	71
6.8.7	<i>Receiving Content on a TunnelStream.....</i>	76
6.8.8	<i>Sending Content on a TunnelStream</i>	76
6.8.9	<i>Closing a Tunnel Stream</i>	78
6.9	Cloud Connectivity	79
6.9.1	<i>Querying Service Discovery</i>	79
6.9.2	<i>OAuth Credential Management</i>	81
6.10	JSON to RWF Protocol Conversion for WebSocket Support.....	83
6.10.1	<i>Consumer and WebSocket Support</i>	84
6.10.2	<i>Interactive Provider and WebSocket Support</i>	86
6.10.3	<i>ReactorJsonConverterOptions</i>	88
6.10.4	<i>ReactorJsonConversionEventCallback Function</i>	89

6.10.5	<i>ReactorServiceNameToldCallback Function</i>	90
6.10.6	<i>ReactorServiceNameToldEvent Class</i>	90
6.10.7	<i>ReactorJsonConversionEvent Class</i>	90
6.11	Reactor Utility Methods	91
6.11.1	<i>General Reactor Utility Methods</i>	91
6.11.2	<i>ReactorChannelInfo Class Members</i>	91
6.11.3	<i>ReactorChannel.ioctl Option Values</i>	91
6.11.4	<i>Debugging for Reactor</i>	91
7	Consuming Data from the Cloud	93
7.1	Overview	93
7.2	Encrypted Connections	93
7.3	Credential Management.....	93
7.4	Version 1 Authentication Using oAuth Password and Refresh_Token	94
7.4.1	<i>Client_ID (AppKey)</i>	94
7.4.2	<i>Obtaining Initial Access and Refresh Tokens</i>	94
7.4.3	<i>Refreshing the Access Token and Sending a Login Reissue</i>	95
7.4.4	<i>Session Management per User Credential</i>	95
7.5	Version 2 Authentication Using oAuth Client Credentials	96
7.5.1	<i>Configuring and Managing Version 2 Credentials</i>	96
7.5.2	<i>Version 2 OAuth Client Credentials Token Lifespan</i>	96
7.6	Service Discovery	97
7.7	Consuming Market Data	98
7.8	HTTP Error Handling for Reactor Token Reissues	98
7.9	Cloud Connection Use Cases	99
7.9.1	<i>Session Management Use Case</i>	99
7.9.2	<i>Disabling the Watchlist</i>	99
7.9.3	<i>Query Service Discovery</i>	99
7.10	Logging of Authentication and Service Discovery Interaction	100
7.10.1	<i>Logged Request Information</i>	100
7.10.2	<i>Logged Response Information</i>	100
8	Administration Domain Models Detailed View	101
8.1	Concepts	101
8.2	Message Base	102
8.2.1	<i>Message Base Members</i>	102
8.2.2	<i>Message Base Method</i>	102
8.2.3	<i>RDM Message Types</i>	103
8.3	RDM Login Domain.....	104
8.3.1	<i>Login Request</i>	104
8.3.2	<i>Login Refresh</i>	107
8.3.3	<i>Login Status</i>	114
8.3.4	<i>Login Close</i>	116
8.3.5	<i>Login Consumer Connection Status</i>	116
8.3.6	<i>Login Round Trip Time Message Use</i>	117
8.3.7	<i>Login Post Message Use</i>	118
8.3.8	<i>Login Ack Message Use</i>	118
8.3.9	<i>Login Attributes</i>	119
8.3.10	<i>Login Message</i>	121
8.3.11	<i>Login Message Utility Method</i>	122
8.3.12	<i>Login Encoding and Decoding</i>	122
8.4	RDM Source Directory Domain.....	127
8.4.1	<i>Directory Request</i>	127
8.4.2	<i>Directory Refresh</i>	129
8.4.3	<i>Directory Update</i>	130

8.4.4	<i>Directory Status</i>	131
8.4.5	<i>Directory Close</i>	132
8.4.6	<i>Directory Consumer Status</i>	133
8.4.7	<i>Directory Service</i>	134
8.4.8	<i>Directory Service Info Filter</i>	135
8.4.9	<i>Directory Service State Filter</i>	137
8.4.10	<i>Directory Service Group Filter</i>	138
8.4.11	<i>Directory Service Load Filter</i>	139
8.4.12	<i>Directory Service Data Filter</i>	140
8.4.13	<i>Directory Service Link Info Filter</i>	141
8.4.14	<i>Directory Service Link</i>	142
8.4.15	<i>Directory Message</i>	143
8.4.16	<i>Directory Message Utility Methods</i>	143
8.4.17	<i>Directory Encoding and Decoding</i>	144
8.5	RDM Dictionary Domain.....	150
8.5.1	<i>Dictionary Request</i>	150
8.5.2	<i>Dictionary Refresh</i>	151
8.5.3	<i>Dictionary Status</i>	152
8.5.4	<i>Dictionary Close</i>	153
8.5.5	<i>Dictionary Messages</i>	153
8.5.6	<i>Dictionary Message: Utility Methods</i>	154
8.5.7	<i>Dictionary Encoding and Decoding</i>	154
8.6	RDM Queue Messages.....	160
8.6.1	<i>Queue Data Message Persistence</i>	160
8.6.2	<i>Queue Request</i>	160
8.6.3	<i>Queue Refresh</i>	161
8.6.4	<i>Queue Status</i>	161
8.6.5	<i>Queue Close</i>	161
8.6.6	<i>Queue Data</i>	162
8.6.7	<i>QueueDataExpired</i>	165
8.6.8	<i>Queue Ack</i>	166
9	Warm Standby Feature	167
9.1	Overview	167
9.2	Warm Standby Modes.....	167
9.3	Warm Standby Configuration and Feature Details.....	169
9.3.1	<i>Configuration Example for a Starting Server and a Standby Server</i>	171
9.4	171
10	Payload Cache Detailed View	172
10.1	Concepts	172
10.2	Payload Cache.....	173
10.2.1	<i>Payload Cache Management</i>	173
10.2.2	<i>Cache Error Handling</i>	173
10.2.3	<i>Payload Cache Instances</i>	174
10.2.4	<i>Managing RDM Field Dictionaries for Payload Cache</i>	174
10.2.5	<i>Payload Cache Utilities</i>	176
10.3	Payload Cache Entries.....	177
10.3.1	<i>Managing Payload Cache Entries</i>	177
10.3.2	<i>Applying Data</i>	178
10.3.3	<i>Retrieving Data</i>	179
	Appendix A Value Added Utilities	182

List of Figures

Figure 1.	Network Diagram Notation	4
Figure 2.	UML Diagram Notation.....	4
Figure 3.	OMM APIs with Value Added Components	5
Figure 4.	Enterprise Transport API Value Added Components.....	6
Figure 5.	ETA Reactor Thread Model	20
Figure 6.	Enterprise Transport API Reactor Application Lifecycle	23
Figure 7.	Flow Chart for writing data using ReactorChannel.Submit(ITransportBuffer...)	55
Figure 8.	Tunnel Stream Illustration	62
Figure 9.	Obtaining an Authentication Token	94
Figure 10.	Login Reissue	95
Figure 11.	Service Discovery	97
Figure 12.	Login Based Warm Standby Order of Events in a Cutover from Active to Standby.....	168
Figure 13.	Service Based Warm Standby Order of Events in a Cutover from Active to Standby	169
Figure 14.	Consumer Application using Cache to Store Payload Data for Item Streams	172

List of Tables

Table 1:	Acronyms and Abbreviations	1
Table 2:	ETA Functionality and ETA Reactor Comparison	21
Table 3:	Error Members	22
Table 4:	Reactor Error Info Codes	22
Table 5:	Reactor Class Members	24
Table 6:	Reactor Creation Method	24
Table 7:	ReactorOptions Class Members	24
Table 8:	ReactorOptions Utility Method	25
Table 9:	ReactorRestProxyOptions Members	25
Table 10:	Reactor Debugging Levels	26
Table 11:	Reactor Destruction Method	27
Table 12:	ReactorChannel Class Members	27
Table 13:	ReactorRole Class Members	29
Table 14:	ReactorRoleType Enumerated Values	29
Table 15:	ConsumerRole Class Members	30
Table 16:	ConsumerRole.dictionaryDownloadMode Enumerated Values	31
Table 17:	OMM Consumer Role Watchlist Options	31
Table 18:	ConsumerRole Utility Method	31
Table 19:	ProviderRole Structure Members	32
Table 20:	ProviderRole Utility Method	32
Table 21:	NIProviderRole Class Members	33
Table 22:	NIProviderRole Utility Method	33
Table 23:	ReactorConnect Method	34
Table 24:	ReactorConnectOptions Structure Members	34
Table 25:	ReactorConnectInfo Class Members	35
Table 26:	ReactorConnectOptions Utility Method	36
Table 27:	Reactor.Accept Function	38
Table 28:	ReactorAcceptOptions Class Members	38
Table 29:	ReactorAcceptOptions Utility Method	38
Table 30:	ReactorChannel.close Function	39
Table 31:	ReactorChannel.dispatch Method	40
Table 32:	ReactorDispatchOptions Members	41
Table 33:	ReactorDispatchOptions Utility Method	41
Table 34:	ReactorCallbackReturnCodes Callback Return Codes	42
Table 35:	ReactorEvent Class Members	42
Table 36:	ReactorChannelEvent	42
Table 37:	ReactorChannelEventType Enumeration Values	43
Table 38:	ReactorChannelEvent Utility Methods	43
Table 39:	ReactorMsgEvent Class Members	45
Table 40:	ReactorMsgEvent Utility Method	45
Table 41:	RDMLoginMsgEvent Member	46
Table 42:	RDMLoginMsgEvent Utility Method	46
Table 43:	RDMDirectoryMsgEvent Class Member	48
Table 44:	RDMDirectoryMsgEvent Utility Method	48
Table 45:	RDMDictionaryMsgEvent Class Member	50
Table 46:	RDMDictionaryMsgEvent Utility Method	50
Table 47:	ReactorChannel.submit(Msg...) Method	51
Table 48:	ReactorSubmitOptions Class Members	52
Table 49:	ReactorChannel.submit(Msg...) Return Codes	52
Table 50:	ReactorRequestMsgOptions Class Members	53
Table 51:	ReactorSubmitOptions Utility Method	53

Table 52:	<code>ReactorChannel</code> Buffer Management Methods	56
Table 53:	<code>ReactorChannel.getBuffer</code> Return Values	57
Table 54:	<code>ReactorChannel.submit</code> Method.....	57
Table 55:	<code>ReactorChannel.submit</code> Return Codes	58
Table 56:	<code>ReactorChannel.packBuffer</code> Method	60
Table 57:	<code>ReactorChannel.packBuffer</code> Return Values	60
Table 58:	<code>TunnelStreamAuthInfo</code> Members.....	63
Table 59:	<code>ReactorChannel.openTunnelStream</code> Method.....	63
Table 60:	<code>TunnelStreamOpenOptions</code>	64
Table 61:	<code>ClassOfService.common</code> Members.....	65
Table 62:	<code>ClassOfService.authentication</code> Members	66
Table 63:	<code>ClassOfService.flowControl</code> Members.....	66
Table 64:	<code>ClassOfService.dataIntegrity</code> Members	67
Table 65:	<code>ClassOfService.guarantee</code> Members	67
Table 66:	Tunnel Stream Callback Methods	68
Table 67:	Tunnel Stream Callback Event Types	69
Table 68:	<code>TunnelStreamRequestEvent</code> Members	72
Table 69:	<code>ReactorChannel.acceptTunnelStream</code> Method.....	72
Table 70:	<code>TunnelStreamAcceptOptions</code> Options.....	73
Table 71:	<code>ReactorChannel.rejectTunnelStream</code> Method.....	73
Table 72:	<code>TunnelStreamRejectOptions</code> Options.....	73
Table 73:	Tunnel Stream Buffer Methods	76
Table 74:	Tunnel Stream Submit Method	76
Table 75:	<code>TunnelStreamSubmitOptions</code> Members	77
Table 76:	TunnelStreamInfo Methods.....	77
Table 77:	Tunnel Closure Method.....	78
Table 78:	<code>Reactor.queryServiceDiscovery</code> Method	79
Table 79:	<code>ReactorServiceDiscoveryOptions</code> Members	79
Table 80:	<code>ReactorDiscoveryTransportProtocol</code> Enumerations	80
Table 81:	<code>ReactorDiscoveryDataFormatProtocol</code> Enumerations	80
Table 82:	<code>ReactorServiceEndpointEvent</code> Members.....	80
Table 83:	<code>ReactorServiceEndpointEvent</code> Members.....	81
Table 84:	<code>ReactorOAuthCredential</code> Class Members.....	81
Table 85:	<code>ReactorOAuthCredentialEvent</code> Members.....	82
Table 86:	<code>ReactorOAuthCredentialRenewal</code> Members	82
Table 87:	ReactorOAuthCredentialRenewal Options.....	83
Table 88:	ReactorOAuthCredentialRenewalMode Enums.....	83
Table 89:	<code>ReactorJsonConverterOptions</code> Class Members.....	88
Table 90:	ReactorServiceNameToIdCallback Parameters	90
Table 91:	<code>ReactorServiceNameToIdEvent</code> Class Members.....	90
Table 92:	<code>ReactorJsonConversionEvent</code> Class Members.....	90
Table 93:	Reactor Utility Methods	91
Table 94:	<code>ReactorChannelInfo</code> Class Members	91
Table 95:	Reactor Methods for Debugging Handling	92
Table 96:	Domains Representations in the Administration Domain Model Value Added Component.....	101
Table 97:	<code>MsgBase</code> Members	102
Table 98:	MsgBase Method	102
Table 99:	Domain Representations Message Types.....	103
Table 100:	<code>LoginRequest</code> Members	104
Table 101:	<code>LoginRequest</code> Flags	106
Table 102:	<code>LoginRequest</code> Utility Method	106
Table 103:	<code>LoginRefresh</code> Members	107
Table 104:	<code>LoginRefresh</code> Flags	108
Table 105:	<code>LoginSupportFeatures</code> Members.....	110
Table 106:	<code>LoginSupportFeaturesFlags</code>	111

Table 107: LoginConnectionConfig Members.....	112
Table 108: LoginConnectionConfig Methods.....	112
Table 109: ServerInfo Members.....	112
Table 110: ServerInfo Flags.....	113
Table 111: ServerInfo Methods.....	113
Table 112: LoginStatus Members	114
Table 113: LoginStatus Flags.....	115
Table 114: LoginClose Member	116
Table 115: LoginConsumerConnectionStatus Members	116
Table 116: LoginConsumerConnectionStatus Flags	116
Table 117: LoginWarmStandbyInfo Members.....	117
Table 118: LoginWarmStandbyInfo Methods	117
Table 119: Login Round Trip Time Members.....	117
Table 120: Login Round Trip Time Flag Enumeration Values	118
Table 121: Login Round Trip Time Utility Methods	118
Table 122: LoginAttrib Members	119
Table 123: LoginAttrib Methods.....	121
Table 124: LoginAttribFlags	121
Table 125: LoginMsg Interfaces	121
Table 126: LoginMsg Utility Method	122
Table 127: Login Encoding and Decoding Methods	122
Table 128: DirectoryRequest Members	127
Table 129: DirectoryRequest Flags.....	128
Table 130: DirectoryRequest Utility Methods.....	128
Table 131: DirectoryRefresh Members	129
Table 132: DirectoryRefresh Flags.....	129
Table 133: DirectoryUpdate Members.....	130
Table 134: DirectoryUpdate Flags	130
Table 135: DirectoryStatus Members.....	131
Table 136: DirectoryStatus Flags.....	131
Table 137: DirectoryStatus Utility Methods	132
Table 138: DirectoryClose Member.....	132
Table 139: DirectoryConsumerStatus Members	133
Table 140: ConsumerStatusService Members.....	133
Table 141: Service Members	134
Table 142: Service Flags	134
Table 143: Service Utility Methods	135
Table 144: ServiceInfo Members	135
Table 145: ServiceInfo Flags.....	136
Table 146: ServiceInfo Utility Methods.....	137
Table 147: ServiceState Members	137
Table 148: ServiceState Flags	137
Table 149: ServiceState Utility Methods.....	138
Table 150: ServiceGroup Members	138
Table 151: ServiceGroup Flags	138
Table 152: ServiceGroup Utility Methods.....	139
Table 153: ServiceLoad Members	139
Table 154: ServiceLoad Flags.....	139
Table 155: ServiceLoad Utility Methods.....	140
Table 156: ServiceData Members	140
Table 157: ServiceData Flags.....	140
Table 158: ServiceData Methods.....	141
Table 159: ServiceLinkInfo Members.....	141
Table 160: ServiceLinkInfo Methods	141
Table 161: ServiceLink Members	142

Table 162: ServiceLink Flags.....	142
Table 163: ServiceLink Methods.....	143
Table 164: DirectoryMsg Interfaces	143
Table 165: DirectoryMsg Utility Methods.....	143
Table 166: Directory Encoding and Decoding Methods	144
Table 167: DictionaryRequest Members	150
Table 168: DictionaryRequest Flag	150
Table 169: DictionaryRefresh Members	151
Table 170: DictionaryRefreshFlags	152
Table 171: DictionaryStatus Members	153
Table 172: DictionaryStatus Flags.....	153
Table 173: DictionaryClose Member	153
Table 174: DictionaryMsg Interfaces	153
Table 175: DictionaryMsg Utility Methods	154
Table 176: Dictionary Encoding and Decoding Methods	154
Table 177: QueueRequest Members	160
Table 178: QueueRefresh Members	161
Table 179: QueueStatus Members	161
Table 180: QueueClose Members.....	161
Table 181: QueueData Members.....	162
Table 182: Queue Data Flag	162
Table 183: Queue Data Message Timeout Codes.....	163
Table 184: Queue Data Message Encoding Methods	163
Table 185: QueueDataExpired Members.....	165
Table 186: Queue Data Message Undeliverable Codes.....	166
Table 187: Queue Ack Members.....	166
Table 188: CacheError Class Members.....	173
Table 189: CacheError Utility Method.....	173
Table 190: Methods for Managing Cache Instances.....	174
Table 191: PayloadCacheConfigOptions Members	174
Table 192: Methods for Setting Dictionary to Cache.....	175
Table 193: PayloadCache Utility Methods.....	176
Table 194: Payload Cache Entry Management Methods.....	177
Table 195: Methods for Applying and Retrieving Cache Entry Data	179
Table 196: Methods for Using the Payload Cursor	179

1 Introduction

1.1 About this Manual

This document is authored by Enterprise Transport API architects and programmers who encountered and resolved many of the issues the reader might face. Several of its authors have designed, developed, and maintained the Enterprise Transport API product and other Refinitiv products which leverage it. As such, this document is concise and addresses realistic scenarios and use cases.

This guide documents the functionality and capabilities of the Enterprise Transport API Java Edition. In addition to connecting to itself, the Enterprise Transport API can also connect to and leverage many different Refinitiv and customer components. If you want the Enterprise Transport API to interact with other components, consult that specific component's documentation to determine the best way to configure for optimal interaction.

1.2 Audience

This manual provides information and examples that aid programmers using the Enterprise Transport API Java Edition Value Added Components. The level of material covered assumes that the reader is a user or a member of the programming staff involved in the design, coding, and test phases for applications which will use the Enterprise Transport API or its Value Added Components. It is assumed that the reader is familiar with the data types, classes, operational characteristics, and user requirements of real-time data delivery networks, and has experience developing products using the Java programming language in a networked environment. Although Transport API Value Added Components offer alternate entry points to Transport API functionality, it is recommended that users are familiar with general Enterprise Transport API usage and interfaces.

1.3 Programming Language

The Enterprise Transport API Components are written to the C, Java, and C# languages. This guide discusses concepts related to the Java Edition. All code samples in this document and all example applications provided with the product are written accordingly.

1.4 Acronyms and Abbreviations

ACRONYM / TERM	MEANING
ADH	Refinitiv Real-Time Advanced Data Hub is the horizontally scalable service component within the Refinitiv Real-Time Distribution System providing high availability for publication and contribution messaging, subscription management with optional persistence, conflation and delay capabilities.
ADS	Refinitiv Real-Time Advanced Distribution Server is the horizontally scalable distribution component within the Refinitiv Real-Time Distribution System providing highly available services for tailored streaming and snapshot data, publication and contribution messaging with optional persistence, conflation and delay capabilities.
API	Application Programming Interface
ASCII	American Standard Code for Information Interchange
DMM	Domain Message Model
Enterprise Message API	The Enterprise Message API (EMA) is an ease of use, open source, Open Message Model API. EMA is designed to provide clients rapid development of applications, minimizing lines of code and providing a broad range of flexibility. It provides flexible configuration with default values to simplify use and deployment. EMA is written on top of the Enterprise Transport API (ETA) utilizing the Value Added Reactor and Watchlist features of ETA.

Table 1: Acronyms and Abbreviations

ACRONYM / TERM	MEANING
Enterprise Transport API (ETA)	Enterprise Transport API is a high performance, low latency, foundation of the Refinitiv Real-Time SDK. It consists of transport, buffer management, compression, fragmentation and packing over each transport and encoders and decoders that implement the Open Message Model. Applications written to this layer achieve the highest throughput, lowest latency, low memory utilization, and low CPU utilization using a binary Refinitiv Wire Format when publishing or consuming content to/from Refinitiv Real-Time Distribution Systems.
GC	Garbage Collection
HTTP	Hypertext Transfer Protocol
HTTPS	Hypertext Transfer Protocol (Secure)
JWK	JSON Web Key. Defined by RFC 7517, a JWK is a JSON formatted public or private key.
JWKS	JSON Web Key Set, This is a set of JWK, placed in a JSON array.
JWT	JSON Web Token. Defined by RFC 7519, JWT allows users to create a signed claim token that can be used to validate a user.
OMM	Open Message Model
QoS	Quality of Service
RDM	Refinitiv Domain Model
RDP	Refinitiv Data Platform: this platform is used for REST interactions. In the context of Real-Time APIs, an API gets authentication tokens and/or queries Service Discovery to get a list of Refinitiv Real-Time — Optimized endpoints using RDP.
Refinitiv Real-Time Distribution System	Refinitiv Real-Time Distribution System is Refinitiv's financial market data distribution platform. It consists of the Refinitiv Real-Time Advanced Distribution Server and Refinitiv Real-Time Advanced Data Hub. Applications written to the Refinitiv Real-Time SDK can connect to this distribution system.
Reactor	The Reactor is a low-level, open-source, easy-to-use layer above the Enterprise Transport API. It offers heartbeat management, connection and item recovery, and many other features to help simplify application code for users.
RFA	Robust Foundation API
RMTES	A multi-lingual text encoding standard
RSSL	Refinitiv Source Sink Library
RTT	Round Trip Time, this definition is used for round trip latency monitoring feature.
RWF	Refinitiv Wire Format, a Refinitiv proprietary binary format for data representation.
SOA	Service Oriented Architecture
SSL	Sink Source Library
UML	Unified Modeling Language
UTF-8	8-bit Unicode Transformation Format

Table 1: Acronyms and Abbreviations

1.5 Additional References and Resources

- Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*
- *API Concepts Guide*
- Enterprise Transport API Java Edition *Developers Guide*
- The [Refinitiv Developer Community](#)

1.6 Documentation Feedback

While we make every effort to ensure the documentation is accurate and up-to-date, if you notice any errors, or would like to see more details on a particular topic, you have the following options:

- Send us your comments via email at ProductDocumentation@refinitiv.com.
- Add your comments to the PDF using Adobe's **Comment** feature. After adding your comments, submit the entire PDF to Refinitiv by clicking **Send File** in the **File** menu. Use the ProductDocumentation@refinitiv.com address.

1.7 Document Conventions

- Typographic
- Document Structure
- Diagrams

1.7.1 Optional, Conditional, and Required

Throughout this manual, all parameters, options, methods, objects, flags, etc., are considered optional unless explicitly marked as **Conditional** or **Required**. If marked as conditional, the item's description will describe the conditions surrounding its use.

1.7.2 Typographic

This document uses the following types of conventions:

- Java classes, methods, in-line code snippets, and types are shown in **Courier New** font.
- Parameters, filenames, tools, utilities, and directories are shown in **Bold** font.
- Document titles and variable values are shown in *italics*.
- When initially introduced, concepts are shown in **Bold, Italics**.
- Longer code examples are shown in Courier New font against a gray background. For example:

```
/* decode contents into the filter list object */
if ((retVal = filterList.decode(deciIter)) >= CodecReturnCodes.SUCCESS)
{
    /* create single filter entry and reuse while decoding each entry */
    FilterEntry filterEntry = CodecFactory.createFilterEntry();
```

1.7.3 Document Structure

- General Concepts
- Detailed Concepts
- Interface Definitions
- Example Code

1.7.4 Diagrams

Diagrams that depict the interaction between components on a network use the following notation:

	Feed Handler, Refinitiv Real-Time server, or other application		Network of multiple servers
	Enterprise Transport API application		Point-to-point connection showing direction of primary data flow
			Point-to-point connection showing direction of client connecting to server
	Multicast network		Data from external source (e.g. consolidated network or exchange)
	Connection to Multicast network, no primary data flow direction		Connection to Multicast network showing direction of primary data flow

Figure 1. Network Diagram Notation

	Object
	Inheritance: object on left is like object on right
	Composition: object on left is made up of some number of objects on right
	Composition: object on left is made up of one object on right

Figure 2. UML Diagram Notation

2 Product Description and Overview

2.1 What is the Enterprise Transport API?

The Enterprise Transport API is a low-level Enterprise Transport API that provides the most flexible development environment to the application developer. It is the foundation on which all Refinitiv OMM-based components are built. The Enterprise Transport API allows applications to achieve the highest throughput and lowest latency available with any OMM API, but requires applications to perform all message encoding/decoding and manage all aspects of network connectivity. The Enterprise Enterprise Transport API, Enterprise Message API, and the Robust Foundation API make up the set of OMM API offerings.




Figure 3. OMM APIs with Value Added Components

The Enterprise Transport API Value Added Components provide alternate entry points for applications to leverage OMM-based APIs with more ease and simplicity. These optional components help to offload much of the connection management code and perform encoding and decoding of some key OMM domain representations. Unlike older domain-based APIs that lock the user into capabilities or ease-of-use into the highest layer of API, Value Added components are independently implemented for use with the Enterprise Transport API and Robust Foundation API in their native languages (Example: Enterprise Transport API in C and Java, Robust Foundation API in C++ and Java). These implementations are then shipped with their respective API products as options for the application developer that may want these additional capabilities.

2.2 What are Enterprise Transport API Value Added Components?

The Value Added Components simplify and compliment the use of the Enterprise Transport API. These components (depicted in green in Figure 4) are offered along side the Enterprise Transport API to maximize the user experience and allow for more intuitive, straight forward, and rapid creation of Enterprise Transport API applications. Applications can write directly to the Enterprise Transport API interfaces or commingle some or all Value Added Components. The choice to leverage these components is up to the application developer; you do not need to use Value Added Components to use the Enterprise Transport API. Using Enterprise Transport API Value Added Components, you can choose and customize the balance between ultra high-performance raw access and ease-of-use feature functionality. Value Added Components are written to the Enterprise Transport API interfaces and are designed to work alongside the Enterprise Transport API. Their interfaces have a similar look and feel to Enterprise Transport API interfaces to provide simple migration and consistent use between all components and the Enterprise Transport API.

All value added components provide fully supported library files ready to build into new or existing Enterprise Transport API applications. Examples and documentation are provided to show the full power and capability of the component for each layer of the Enterprise Transport API.

Some value added components provide buildable source code¹ to allow for customization and modification to suit specific user needs. This source code serves the following purposes:

- Clients may want to provide their own implementation of the component. Rather than starting from scratch, clients can modify the component to jump start their development efforts.

NOTE: If a client customizes a component's code, the client is responsible for its support and maintenance.

- Clients might want to build a new component that has similar behaviors to an existing component. Clients can leverage the code of one component to jump start their development efforts.
- Clients may want to collaborate in troubleshooting or suggesting improvements to the component for everyone's benefit.




Figure 4. Enterprise Transport API Value Added Components

1. Refinitiv fully supports the use of its pre-built library files. Provided source code can help with user troubleshooting and debugging. However, the user, not Refinitiv, is responsible for supporting any modifications to the provided source.

2.3 Transport API Reactor

The **Enterprise Transport API reactor** is a connection management and event processing component that can significantly reduce the amount of code an application must write to leverage OMM in its own functions and to connect to other OMM-based devices. Consumer, interactive provider, and non-interactive provider applications can use the reactor and leverage it in managing consumer and non-interactive provider start-up processes, including user log in, source directory establishment, and dictionary download. The reactor also supports dispatching of events to user-implemented callback functions. In addition, it handles the flushing of user-written content and manages network pings on the user's behalf. The connection recovery feature allows the reactor to automatically recover from disconnects. Value Added domain representations are coupled with the reactor, allowing domain specific callbacks to be presented with their respective domain representation for easier, more logical access to content. For more information, refer to Chapter 6. This component depends on the Value Added Administration Domain Model Representation component, the Value Added Utilities, Enterprise Transport API Java Transport Package, and Enterprise Transport API Java Codec Package.

2.4 OMM Consumer Watchlist

The **Reactor** features a per-channel watchlist that provides a wealth of functionality for OMM consumer applications. The watchlist automatically performs various recovery behaviors for which developers would normally need to account.

The watchlist supports consuming from TCP-based connections (`ConnectionTypes.SOCKET`, `ConnectionTypes.WEBSOCKET`, etc.).

For details on configuring the **Reactor** to enable the consumer watchlist, refer to Section 6.3.2.

2.4.1 Data Stream Aggregation and Recovery

The watchlist automatically recovers data streams in response to failure conditions, such as disconnects and unavailable services, so that applications do not need special handling for these conditions. As conditions are resolved, the watchlist will re-request items on the application's behalf. Applications can also use this method to request data before a connection is fully established.

To recover from disconnects using a watchlist, enable the reactor's connection recovery. Options to reconnect disconnected channels are detailed in Section 6.4.1.2.

For efficient bandwidth usage, the watchlist also combines multiple requests for the same item into a single stream and forwards response messages to each requested stream as appropriate.

2.4.2 Additional Features

The watchlist provides additional features for convenience:

- Group and Service Status Fanout: The **Reactor** maintains a directory stream to receive service updates. As group status messages or service status messages are received, the **Reactor** forwards the status to all affected streams via `StatusMsgs`.
- Quality of Service Range Matching: The **Reactor** will accept and aggregate item requests that specify a range of `Qos`, or requests that do not specify a `Qos`. After comparing these requests with the quality of service from the providing service, the watchlist uses the best matching quality of service.
- Support for Enhanced Symbol List Behaviors: The **Reactor** supports data streams when requesting a Symbol List item. For details on requesting Symbol list data streams, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.
- Support for Batch Requests: The **Reactor** will accept batch requests regardless of whether the connected provider supports them.

2.4.3 Usage Notes

Applications should note the following when enabling the watchlist:

- The application must use the `ReactorChannel.submit(Msg)` and `ReactorChannel.submit(MsgBase)` methods to send messages. It cannot use `ReactorChannel.submit(TransportBuffer)`.
- Only one login stream should be opened per `ReactorChannel`.
- To prevent unnecessary bandwidth use, the watchlist will not recover a dictionary request after a complete refresh is received.
- As private streams are intended for content delivery between two specific points, the watchlist does not aggregate nor recover them.
- The `ConsumerRole.dictionaryDownloadMode` option is not supported when the watchlist is enabled.

2.5 Administration Domain Model Representations

The **Administration Domain Model Representations** are RDM-specific representations of the OMM administrative domain models. This Value Added Component contains classes and interfaces that represent the messages within the Login, Source Directory, and Dictionary domains. All classes follow the formatting and naming specified in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*, so access to content is logical and specific to the content being represented. This component also handles all encoding and decoding functionality for these domain models, so the application needs only to manipulate the message's class members to send or receive this content. This not only significantly reduces the amount of code an application needs to interact with OMM devices (i.e., Refinitiv Real-Time Distribution System infrastructure), but also ensures that encoding/decoding for these domain models follow OMM-specified formatting rules. Applications can use this Value Added Component directly to help with encoding, decoding, and representation of these domain models. When using the Enterprise Transport API Reactor, this component is embedded to manage and present callbacks with a domain-specific representation of content. For more information, refer to Chapter 8. This component depends on the Enterprise Transport API Java Codec Package.

2.6 Value Added Utilities

The Value Added Utilities are a collection of common classes, mainly used by the Enterprise Transport API Reactor. Included is a selectable bidirectional queue used to communicate events between the Reactor and Worker threads. Other Value Added Utilities include a simple queue along with iterable and concurrent versions of it.

2.7 Payload Cache

Applications can leverage the OMM payload cache feature. Using the payload cache, an application can maintain a local store of the OMM container data it consumes, publishes, or transforms. The cache maintains the latest values of the OMM data entries: container values update to reflect the most recent refresh and update message payloads whenever the application receives them. The Enterprise Transport API retrieves data from the cache entry in the form of an encoded OMM container. The payload cache is independent of other Value Added components, and only requires the Enterprise Transport API CSharp Codec Package. Only library files are available for the cache component.

3 Building an OMM Consumer

3.1 Overview

This chapter provides an overview of how to create an OMM consumer application using the ETA Reactor and Administration Domain Model Representation Value Added Components. The Value Added Components simplify the work done by an OMM consumer application when establishing a connection to other OMM interactive provider applications, including Refinitiv Real-Time Distribution System, Refinitiv Data Feed Direct, and Refinitiv Real-Time — Optimized. After the Reactor indicates that the connection is ready, an OMM consumer can then consume (i.e., send data requests and receive responses) and publish data (i.e., post data).

The general process can be summarized by the following steps.

- Leverage existing or create new **Reactor**
- Implement callbacks and populate role
- Establish connection using **Reactor.connect**
- Issue requests and/or post information
- Log out and shut down

The **Consumer** example application, included with the ETA product, provides one implementation of an OMM consumer application that uses the ETA Value Added Components. The application is written with simplicity in mind and demonstrates usage of the ETA and ETA Value Added Components. Portions of functionality have been abstracted and can easily be reused, though you might need to modify it to achieve your own unique performance and functionality goals.

3.2 Leverage Existing or Create New Reactor

The **Reactor** can manage one or multiple **ReactorChannel** structures. This functionality allows the application to associate OMM consumer connections with an existing **Reactor**, having it manage more than one connection, or to create a new **Reactor** to use with the connection.

To create a new **Reactor**, the application must use the static method **ReactorFactory.createReactor** of the **Reactor** class. This will create any necessary memory and threads that the **Reactor** uses to manage **ReactorChannels** and their content flow. If the application is using an existing **Reactor**, there is nothing additional to do.

For more information about the **Reactor** and its creation, refer to Section 6.2.1.

3.3 Implement Callbacks and Populate Role

Before creating the OMM consumer connection, the application needs to specify callback functions to use for all inbound content. The callback functions are specified on a per **ReactorChannel** basis so each channel can have its own unique callback functions or existing callback functions can be specified and shared across multiple **ReactorChannels**.

Use of a **Reactor** requires the use of several callback functions. The application must have the following:

- **reactorChannelEventCallback**, which returns information about the **ReactorChannel** and its state (e.g., connection up)
- **DefaultMsgCallback**, which processes all data not handled by other optional callbacks.

In addition to the required callbacks, an OMM consumer can specify several administrative domain-specific callback functions. Available domain-specific callbacks include:

- **RDMLoginMsgCallback**, which processes all data for the RDM Login domain.
- **RDMDirectoryMsgCallback**, which processes all data for the RDM Source Directory domain.
- **RDMDictionaryMsgCallback**, which processes all data for the RDM Dictionary domain.

The **ConsumerRole** object should be populated with all callback information for the **ReactorChannel**.

The **ConsumerRole** allows the application to provide login, directory, and dictionary request information. This can be initialized with default information. The callback functions are specified on the **ConsumerRole** class or with specific information according to the application and user. The **Reactor** will use this information when starting up the **ReactorChannel**.

For more information about the **ConsumerRole**, refer to Section 6.3.1. For information about the various callback functions and their specifications, refer to Section 6.6.2.

3.4 Establish Connection using Reactor.connect

After populating the **ConsumerRole**, the application can use **Reactor.connect** to create a new outbound connection.

Reactor.connect will create an OMM consumer-type connection using the provided configuration and role information.

After establishing the underlying connection, a channel event is returned to the application's **reactorChannelEventCallback**; this provides the **ReactorChannel** and the state of the current connection. At this point, the application can begin using the **ReactorChannel.dispatch** function to dispatch directly on this **ReactorChannel**, or use **ReactorChannel.dispatch** to dispatch across all channels associated with the **Reactor**.

The **Reactor** will use the login, directory, and dictionary information specified on the **ConsumerRole** to perform all channel initialization for the user. After a user has logged in, received a source directory response, and downloaded field dictionaries, a channel event is returned to inform the application that the connection is ready.

The **Reactor.connect** function is described in Section 6.4.1.1. Dispatching is described in Section 6.6.

3.5 Issue Requests and/or Post Information

After the **ReactorChannel** is established, the channel can be used to request additional content. When issuing the request, the consuming application can use the **serviceId** of the desired service, along with the stream's identifying information. Requests can be sent for any domain using the formats defined in that domain model specification. Domains provided by Refinitiv are defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*. This content will be returned to the application via the **IDefaultMsgCallback**.

At this point, an OMM consumer application can also post information or forward generic messages to capable provider applications. All content requested, received, or posted is encoded and decoded using the ETA Codec Package described in the Enterprise Transport API Java Edition *Developers Guide*.

3.6 Log Out and Shut Down

When the consumer application is done retrieving, forwarding, or posting content, the consumer can close the **ReactorChannel** by calling **ReactorChannel.Close**. This will close all item streams and log out the user. Prior to closing the **ReactorChannel**, the application should release any unwritten pool buffers to ensure proper memory cleanup.

If the application is done with the **Reactor**, the **Reactor.Shutdown** function can be used to shutdown and clean up any **Reactor** resources.

- Closing a **ReactorChannel** is described in Section 6.4.2.
- Shutting down a **Reactor** is described in Section 6.2.2.

3.7 Additional Consumer Details

The following locations provide specific details about using OMM consumers, the ETA, and ETA Value Added Components:

- The **Consumer** application demonstrates one way of implementing of an OMM consumer application that uses ETA Value Added Components. The application's source code and Javadoc contain additional information about specific implementation and behaviors.
- Chapter 6 provides a detailed look at the ETA Reactor.
- Chapter 8 provides more information about the Administration Domain Model Representations.
- The Enterprise Transport API Java Edition *Developers Guide* provides specific ETA encoder/decoder and transport usage information.
- The Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide* provides specific information about the Domain Message Models used by this application type.

4 Building an OMM Interactive Provider

4.1 Overview

This chapter provides a high-level description of how to create an OMM interactive provider application using the ETA Reactor and Administration Domain Model Representation Value Added Components. An OMM interactive provider application opens a listening socket on a well-known port allowing OMM consumer applications to connect. The ETA Value Added Components simplify the work done by an OMM interactive provider application when accepting connections and handling requests from OMM consumers.

The following steps summarize this process:

- Leverage an existing **Reactor**, or create a new one
- Create a **Server**
- Implement callbacks and populate role
- Associate incoming connections using **Reactor.Accept**
- Perform login process
- Provide source directory information
- Provide necessary dictionaries
- Handle requests and post messages
- Dispatch Round Trip Time messages
- Disconnect consumers and shut down

Included with the ETA product, the **Provider** example application provides one way of implementing an OMM interactive provider application that uses the ETA Value Added Components. The application is written with simplicity in mind and demonstrates the use of the ETA and ETA Value Added Components. Portions of the functionality are abstracted for easy reuse, though you might need to customize it to achieve your own unique performance and functionality goals.

4.2 Leverage Existing or Create New Reactor

The **Reactor** can manage one or multiple **ReactorChannel** objects. This allows the application to choose to associate OMM provider connections with an existing **Reactor**, have it manage more than one connection, or create a new **Reactor** to use with the connection.

If the application is creating a new **Reactor**, the **Reactor.CreateReactor** method is used. This will create any necessary memory and threads that the **Reactor** uses to manage **ReactorChannels** and their content flow. If the application is using an existing **Reactor**, there is nothing additional to do.

Detailed information about the **Reactor** and its creation are available in Section 6.2.1.

4.3 Create a Server

The first step of any ETA Interactive Provider application is to establish a listening socket, usually on a well-known port so that consumer applications can easily connect. The provider uses the **Transport.Bind** method to open the port and listen for incoming connection attempts. This uses the standard ETA Transport functionality described in the Enterprise Transport API Java Edition *Developers Guide*.

Whenever an OMM consumer application attempts to connect, the provider will use the **Server** and associate the incoming connections with a **Reactor**, which will accept the connection and perform any initialization as described in Section 4.4 and Section 4.5.

4.4 Implement Callbacks and Populate Role

Before accepting an incoming connection with an OMM provider, the application needs to specify callback methods to use for all inbound content. Callback methods are specified on a per **ReactorChannel** basis so each channel can have its own unique callback methods or existing callback methods can be specified and shared across multiple **ReactorChannels**.

The following callback methods are required for use with a **Reactor**:

- **IReactorChannelEventCallback**, which returns information about the **ReactorChannel** and its state (e.g., connection up)
- **IDefaultMsgCallback**, which processes all data not handled by other optional callbacks.

In addition to the required callbacks, an OMM provider can specify several administrative domain-specific callback methods. Available domain-specific callbacks are:

- **IRDMLLoginMsgCallback**, which processes all data for the RDM Login domain.
- **IDirectoryMsgCallback**, which processes all data for the RDM Source Directory domain.
- **IDictionaryMsgCallback**, which processes all data for the RDM Dictionary domain.

The **ProviderRole** object should be populated with all callback information for the **ReactorChannel**.

Detailed information about the **ProviderRole** is in Section 6.3.1. Information about the various callback methods and their specifications are available in Section 6.6.2.

4.5 Associate Incoming Connections Using Reactor.accept

After the **ProviderRole** is populated, the application can use **Reactor.Accept** to accept a new inbound connection. **Reactor.Accept** will accept an OMM provider connection from the passed-in **IServer** using provided configuration and role information.

When the underlying connection is established, a channel event is returned to the application's **ReactorChannelEventCallback**; this will provide the **ReactorChannel** and indicate the current connection state. At this point, the application can begin using the **Reactor.Dispatch** method to dispatch directly on this **ReactorChannel**, or continue using **Reactor.Dispatch** to dispatch across all channels associated with the **Reactor**.

The **Reactor** will perform all channel initialization and pass any administrative domain information to the application via the callbacks specified with the **ProviderRole**.

- For more details on the **Reactor.Accept** function, refer to Section 6.4.1.6.
- For more details on dispatching, refer to Section 6.6.

4.6 Perform Login Process

Applications authenticate with one another using the Login domain model. An OMM interactive provider must handle consumer Login request messages and supply appropriate responses. Login information will be provided to the application via the **IRDMLLoginMsgCallback**, when specified on the **ProviderRole**.

After receiving a Login request, an interactive provider can perform any necessary authentication and permissioning.

- If the interactive provider grants access, it should send an **LoginRefresh** to convey that the user successfully connected. This message should indicate the feature set supported by the provider application.
- If the interactive provider denies access, it should send an **LoginStatus**, closing the connection and informing the user of the reason for denial.

Login messages can be encoded and decoded using themessages' **Encode** and **Decode** functions. More details and code examples are in Section 8.3.

All content requested, received, or posted is encoded and decoded using the ETA Codec Package described in the Enterprise Transport API Java Edition *Developers Guide*.

Information about the Login domain and expected content formatting is available in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

4.7 Provide Source Directory Information

The Source Directory domain model conveys information about all available services in the system. An OMM consumer typically requests a Source Directory to retrieve information about available services and their capabilities. This includes information about supported domain types, the service's state, the quality of service, and any item group information associated with the service. Refinitiv recommends that at a minimum, an interactive provider supply the Info, State, and Group filters for the Source Directory.

- The Source Directory Info filter contains the name and **ServiceId** for each available service. The interactive provider should populate the filter with information specific to the services it provides.
- The Source Directory State filter contains status information for the service informing the consumer whether the service is Up (available), or Down (unavailable).
- The Source Directory Group filter conveys item group status information, including information about group states, as well as the merging of groups. If a provider determines that a group of items is no longer available, it can convey this information by sending either individual item status messages (for each affected stream) or a Directory message containing the item group status information. Additional information about item groups is available in the Enterprise Transport API Java Edition *Developers Guide*.

Login messages can be encoded and decoded using the **DirectoryMsg** messages' **Encode** and **Decode** methods. More details and code examples are in Section 8.4.

All content requested, received, or posted is encoded and decoded using the ETA Codec Package described in the Enterprise Transport API Java Edition *Developers Guide*.

Information about the Source Directory domain and expected content formatting is available in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*

4.8 Provide or Download Necessary Dictionaries

Some data requires the use of a dictionary for encoding or decoding. The dictionary typically defines type and formatting information, and tells the application how to encode or decode information. Content that uses the **FieldList** type requires the use of a field dictionary (usually the Refinitiv **RDMFieldDictionary**, though it can instead be a user-defined or modified field dictionary).

The Source Directory message should notify the consumer about dictionaries needed to decode content sent by the provider. If the consumer needs a dictionary to decode content, it is ideal that the interactive provider application also make this dictionary available to consumers for download. The provider can inform the consumer whether the dictionary is available via the Source Directory.

If consuming from a Refinitiv Real-Time Advanced Data Hub and providing content downstream, a provider application can also download the RWFFId and RWFEnum dictionaries. Using these dictionaries, the ETA can retrieve appropriate dictionary information for providing field list content. A provider can use this feature to ensure they are using the appropriate version of the dictionary or to encode data. A Refinitiv Real-Time Advanced Data Hub that supports provider dictionary downloads sends a Login request message containing the **SupportProviderDictionaryDownload** login element. The ETA sends the dictionary request using the Dictionary domain model. For details on using the Login domain and expected message content, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

Dictionary messages can be encoded and decoded using the messages' **Encode** and **Decode** methods. More details and code examples are in . Dictionary requests will be provided via the **IDictionaryMsgCallback**, when specified on the **ProviderRole**.

Whether loading a dictionary from file or requesting it from a Refinitiv Real-Time Advanced Data Hub, the ETA offers several utility functions for loading, downloading, and managing a properly-formatted field dictionary. The ETA also has utility functions that help the provider encode into an appropriate format for downloading or decoding downloaded dictionaries.

- All content requested, received, or posted is encoded and decoded using the ETA Codec Package described in the Enterprise Transport API Java Edition *Developers Guide*.

- Information about the Dictionary domain, dictionary utility functions, and expected content formatting is available in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

4.9 Handle Requests and Post Messages

A provider can receive a request for any domain, though this should typically be limited to the domain capabilities indicated in the Source Directory. When a request is received, the provider application must determine if it can satisfy the request by:

- Comparing **MsgKey** identification information
- Determining whether it can provide the requested quality of service
- Ensuring that the consumer does not already have a stream open for the requested information

If a provider can service a request, it should send appropriate responses. However, if the provider cannot satisfy the request, the provider should send an **StatusMsg** to indicate the reason and close the stream. All requests and responses should follow specific formatting as defined in the domain model specification. The Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide* defines all domains provided by Refinitiv. This content will be returned to the application via the **IDefaultMsgCallback**.

The provider can specify that it supports post messages via the **LoginRefresh**. If a provider application receives a post message, the provider should determine the correct handling for the post. This depends on the application's role in the system and might involve storing the post in its cache or passing it farther up into the system. If the provider is the destination for the post, the provider should send any requested acknowledgments, following the guidelines described in the Enterprise Transport API Java Edition *Developers Guide*. Any posted content will be returned to the application via the **IDefaultMsgCallback**.

All content requested, received, or posted is encoded and decoded using the ETA Codec Package as described in the Enterprise Transport API Java Edition *Developers Guide*.

4.10 Dispatch Round Trip Time Messages

Optionally, a provider can send a Round Trip Time message to gather Round Trip Time statistics. While the ETA does not regulate rules for implementing the Round Trip Time message, the ETA provides several examples for applying this feature in provider applications. Generally, if the provider wants to support the Round Trip Time feature, the provider must provide methods for sending generic Round Trip Time messages to a consumer and extend callback methods for Round Trip Time calculation.

For detailed information, refer to the Enterprise Transport API Java Edition *RDM Usage Guide*.

4.11 Disconnect Consumers and Shut Down

If the **Reactor** application must shut down, it can either leave consumer connections intact or shut them down. If the provider decides to close consumer connections, the provider should send an **StatusMsg** on each connection's Login stream closing the stream. At this point, the consumer should assume that its other open streams are also closed.

It can then close the **ReactorChannels** by calling **ReactorChannel.Close**. Prior to closing the **ReactorChannel**, the application should release any unwritten pool buffers to ensure proper memory cleanup.

If the application is done with the **Reactor**, the **Reactor.Shutdown** method can be used to shutdown and cleanup any **Reactor** resources.

- Closing a **ReactorChannel** is described in Section 6.4.2.
- Shutting down a **Reactor** is described in Section 6.2.2.

4.12 Additional Interactive Provider Details

For specific details about OMM interactive providers, the ETA, and ETA Value Added Component use, refer to the following locations:

- The **Provider** application demonstrates one implementation of an OMM interactive provider application that uses ETA Value Added Components. The application's source code and Javadoc have additional information about specific implementation and behaviors.
- Chapter 6 provides a detailed look at the ETA Reactor.
- Chapter 8 provides more information about the Administration Domain Model Representations.
- The Enterprise Transport API Java Edition *Developers Guide* provides specific ETA encoder/decoder and transport usage information.
- The Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide* provides specific information about the Domain Message Models used by this application type.

5 Building an OMM Non-Interactive Provider

5.1 Building an OMM Non-Interactive Provider Overview

This chapter provides an overview of how to create an OMM non-interactive provider application using the ETA Reactor and Administration Domain Model Representation Value Added Components. The Value Added Components simplify the work done by an OMM non-interactive provider application when establishing a connection to a Refinitiv Real-Time Advanced Data Hub. After the reactor indicates that the connection is ready, an OMM non-interactive provider can publish information into the Refinitiv Real-Time Advanced Data Hub cache without needing to handle requests for the information. The Refinitiv Real-Time Advanced Data Hub and other Refinitiv Real-Time Distribution System components can cache the information and provide it to any OMM consumer applications that indicate interest.

The general process can be summarized by the following steps.

- Leverage existing or create new **Reactor**
- Implement callbacks and populate role
- Establish connection using **ReactorConnect**
- Perform dictionary download
- Provide content
- Log out and shut down

The **NIProvider** example application, included with the ETA product, provides one implementation of an OMM non-interactive provider application that uses the ETA Value Added Components. The application is written with simplicity in mind and demonstrates usage of the ETA and ETA Value Added Components. Portions of functionality have been abstracted and can easily be reused, though you might need to modify it to achieve your own unique performance and functionality goals.

5.2 Leverage Existing or Create New Reactor

The **Reactor** can manage one or multiple **ReactorChannel** objects. This allows the application to choose to associate OMM non-interactive provider connections with an existing **Reactor**, having it manage more than one connection, or to create a new **Reactor** to use with the connection.

If the application is creating a new **Reactor**, the **CreateReactor** method is used. This will create any necessary memory and threads that the **Reactor** uses to manage **ReactorChannel** and their content flow. If the application is using an existing **Reactor**, there is nothing more to do.

Detailed information about the **Reactor** and its creation are available in Section 6.2.1.

5.3 Implement Callbacks and Populate Role

Before creating the OMM non-interactive provider connection, the application needs to specify callback methods to use for all inbound content. Callback methods are specified on a per **ReactorChannel** basis so each channel can have its own unique callback methods or existing callback methods can be specified and shared across multiple **ReactorChannels**.

A **Reactor** requires the use of the following callback methods:

- **IReactorChannelEventCallback**, which returns information about the **ReactorChannel** and its state (e.g., connection up)
- **IDefaultMsgCallback**, which processes all data not handled by other optional callbacks.

Additionally, an OMM non-interactive provider can specify the administrative domain-specific callback method **IRDMLoginMsgCallback**, which processes all data for the RDM Login domain.

The **NIPrviderRole** object should be populated with all callback information for the **ReactorChannel**. **NIPrviderRole** allows the application to provide login request and initial directory refresh information. This can be initialized with default information. Callback methods are specified on the **NIPrviderRole** object or with specific information according to the application and user. The **Reactor** will use this information when starting up the **ReactorChannel**.

- For detailed information on the **NIPrviderRole**, refer to Section 6.3.1.
- For information on the various callback methods and their specifications, refer to Section 6.6.2.

5.4 Establish Connection using Reactor.connect

After populating the **NIPrviderRole**, the application can use **Reactor.Connect** to create a new outbound connection.

Reactor.Connect will create an OMM non-interactive provider type connection using the provided configuration and role information.

When the underlying connection is established, a channel event will be returned to the application's **IReactorChannelEventCallback**, which provides the **ReactorChannel** and indicates the current connection state. At this point, the application can begin using the **Reactor.Dispatch** method to dispatch directly on this **ReactorChannel**, or use **Reactor.Dispatch** to dispatch across all channels associated with the **Reactor**.

The **Reactor** will use the login and directory information specified on the **NIPrviderRole** to perform all channel initialization for the user. After the user is logged in and has sent a source directory response, a channel event is returned to inform the application that the connection is ready.

- For further details on the **Reactor.Connect** method, refer to Section 6.4.1.1.
- For further details on dispatching, refer to Section 6.6.

5.5 Download the Dictionary

If connected to a supporting Refinitiv Real-Time Advanced Data Hub, an OMM non-interactive provider can download the RWFFId and RWFEnum dictionaries to retrieve the appropriate dictionary information for providing field list content. An OMM non-interactive provider can use this feature to ensure they use the appropriate version of the dictionary or to encode data. To support the Provider Dictionary Download feature, the Refinitiv Real-Time Advanced Data Hub sends a Login response message containing the **SupportProviderDictionaryDownload** login element. The dictionary request is sent using the Dictionary domain model.

The ETA offers several utility functions for downloading and managing a properly-formatted field dictionary. The provider can also use utility functions to encode the dictionary into an appropriate format for downloading or decoding.

For details on using the Login domain, expected message content, and available dictionary utility functions, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

5.6 Provide Content

After the **ReactorChannel** is established, it can begin pushing content to the Refinitiv Real-Time Advanced Data Hub. Each unique information stream should begin with an **RefreshMsg**, conveying all necessary identification information for the content. Because the provider instantiates this information, a negative value **streamId** should be used for all streams. The initial identifying refresh can be followed by other status or update messages.

All content is encoded and decoded using the ETA Java Codec Package described in the Enterprise Transport API Java Edition *Developers Guide*.

5.7 Log Out and Shut Down

When the Consumer application is done retrieving or posting content, it can close the **ReactorChannel** by calling **ReactorChannel.Close**. This will close all item streams and log out the user. Prior to closing the **ReactorChannel**, the application should release any unwritten pool buffers to ensure proper memory cleanup.

If the application is done with the **Reactor**, the **Reactor.Shutdown** method can be used to shutdown and cleanup any **Reactor** resources.

- For details on closing a **ReactorChannel**, refer to Section 6.4.2.
- Shutting down a **Reactor** is described in Section 6.2.2.

5.8 Additional Non-Interactive Provider Details

The following locations discuss specific details about using OMM non-interactive providers and the ETA:

- The **NIProvider** application demonstrates one implementation of an OMM non-interactive provider application that uses ETA Value Added Components. The application's source code and documentation have additional information about the specific implementation and behaviors.
- Chapter 6 provides a detailed look at the ETA Reactor.
- Chapter 8 provides more information about Administration Domain Model Representations.
- The Enterprise Transport API Java Edition *Developers Guide* provides specific ETA encoder/decoder and transport usage information.
- The Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide* provides specific information about the Domain Message Models used by this application type.

6 Reactor Detailed View

6.1 Concepts

The **ETA Reactor** is a connection management and event processing component that can significantly reduce the amount of code an application must write to leverage OMM. This component helps simplify many aspects of a typical ETA application, regardless of whether the application is an OMM consumer, OMM interactive provider, or OMM non-interactive provider. The ETA Reactor can help manage consumer and non-interactive provider start up processing, including user log in, source directory establishment, and dictionary download. It also allows for dispatching of events to user-implemented callback functions, handles flushing of user-written content, and manages network pings on the user's behalf. Value Added domain representations are coupled with the reactor, allowing domain-specific callbacks to be presented with their respective domain representation for easier, more logical access to content. For a list and comparison of ETA and ETA Reactor functionalities, refer to Section 6.1.1.

The ETA Reactor internally depends on the Administration Domain Model Representation component. This allows the user to provide and consume the administrative RDM types in a more logical format. This additionally hides encoding and decoding of these domains from the Reactor user, all interaction is via a simple structural representation. More information about the Administration Domain Model Representation value added component is available in Chapter 8. The ETA Reactor also leverages several utility components, contained in the Value Added Utilities. This includes an iterable queue and a selectable bidirectional queue used to communicate events between the Reactor and Worker threads.

The ETA Reactor helps to manage the life-cycle of a connection on the user's behalf. When a channel is associated with a reactor, the reactor performs all necessary transport level initialization and alerts the user, via a callback, when the connection is up, ready for use, or is down. An application can simultaneously run multiple unique reactor instances, where each reactor instance can associate and manage a single channel or multiple channels. This functionality allows users to quickly and easily horizontally scale their application to leverage multi-core systems or distribute content across multiple connections.

Each instance of the ETA Reactor leverages multiple threads to help manage inbound and outbound data efficiently. The following figure illustrates a high-level view of the reactor threading model.




Figure 5. ETA Reactor Thread Model

There are two main threads associated with each ETA Reactor instance. The application thread is the main driver of the reactor; all event dispatching (e.g., reading), callback processing, and submitting of data to the ETA is done from this thread. Such architecture reduces latency and simplifies any threading model associated with user-defined callback methods – because callbacks happen from the application thread, a single-threaded application does not need to have additional mutex locking. The ETA Reactor also leverages an internal worker thread. The worker thread flushes any queued outbound data and manages outbound network pings for all channels associated with the Reactor. It also attempts to recover any connections that are lost.

The application drives the reactor with the use of a dispatch method. The dispatch method reads content from the network, performs some light processing to handle inbound network pings, and provides the information to the user through a series of per-channel, user-defined callback methods. Callback methods are separated based on whether they are reactor callbacks or channel callbacks. Channel callbacks are separated by domain, with a default callback where all unhandled domains or non-OMM content are provided to the user. The application can choose whether to dispatch on a single channel or across all channels managed by the reactor. The application can leverage an I/O notification mechanism (e.g. select, poll) or periodically call dispatch – it is all up to the user.

6.1.1 Functionality: Enterprise Transport API Versus Enterprise Transport API Reactor

FUNCTIONALITY	ETA	ETA REACTOR
Automatic Flushing of Data	***	X
Controlled Fragmentation and Assembly of Large Messages	X	X
Controlled Locking / Threading Model	X	X
Controlled Message Buffers with Ability to Change During Runtime	X	X
Controlled Message Packing	X	X
Downloading Field Dictionary	***	X
Loading Field Dictionary File	***	X
Network Ping Management	***	X
Programmatic Configuration	X	X
Programmatic Logging	X	X
Requesting Source Directory	***	X
Round Trip Latency Monitoring	***	For particular roles: • c: consumer • nip: Non-Interactive provider • p: provider
Session Management	***	X
Support for Unified and Segmented Network Connection Types	X	X
User-Defined Callbacks for Data	***	X
User Login	***	X

***: ETA users can implement this functionality themselves. They can also use or modify the ETA Reactor functionality.

Table 2: ETA Functionality and ETA Reactor Comparison

6.1.2 Reactor Error Handling

The **ReactorErrorInfo** object is used to return error or warning information to the application. This can be returned from the various reactor methods as well as part of a callback method.

- If returned directly from a reactor method: an error occurred while processing in that method.
- If returned as part of a callback method: an error has occurred on one of the channels managed by the reactor.

ReactorErrorInfo members are as follows:

PROPERTY	DESCRIPTION
rsslErrorInfoCode	An informational code about this error. Indicates whether it reports a failure condition or is intended to provide non-failure-related information to the user. For details on available codes, refer to Table 21.
error	Returns an error object (i.e., the underlying error information from the Enterprise Transport API). error includes a pointer to the Channel on which the error occurred, both a Enterprise Transport API and a system error number, and more descriptive error text. The error and its values are described in the Enterprise Transport API Java Edition <i>Developers Guide</i> .
location	Provides information about the file and line on which the error occurred. Detailed error text is provided via the error portion of this object.

Table 3: Error Members

6.1.3 Reactor Error Info Codes

It is important that the application monitors return values from the **Reactor** callbacks and methods. Error codes indicate whether the returned **ReactorErrorInfo** is the result of a failure condition or is simply providing information regarding a successful operation.

RETURN CODE	DESCRIPTION
FAILURE	A general failure has occurred. The ReactorErrorInfo code contains more information about the specific error.
PARAMETER_OUT_OF_RANGE	Indicates that a parameter was out of range.
PARAMETER_INVALID	Indicates that a parameter was invalid.
SUCCESS	Indicates a success code. Used to inform the user of success and provide additional information.
WRITE_CALL AGAIN	This is a transport success code. ReactorChannel.submit is fragmenting the buffer and needs to be called again with the same buffer. In this case, Write was unable to send all fragments with the current call and must continue fragmenting content.

Table 4: Reactor Error Info Codes

6.1.4 Enterprise Transport API Reactor Application Lifecycle

The following figure depicts the typical lifecycle of an application using the Enterprise Transport API Reactor, as well as associated method calls. Subsequent sections in this document provide more detailed information.




Figure 6. Enterprise Transport API Reactor Application Lifecycle

6.2 Reactor Use

This section describes use of `Reactor`. The `Reactor` manages `ReactorChannels` (described in Section 6.3). An understanding of both constructs is necessary for application writers. Reactor uses the class members described in Table 5.

NOTE: An application can leverage multiple `Reactor` instances to scale across multiple cores and distribute their `ReactorChannels` as needed.

CLASS PROPERTY	DESCRIPTION
reactorChannel	The reactor's internal channel used for Reactor specific events to communicate with the worker thread. The application must register this ReactorChannel's selectable channel with its selector if using select notification. All ReactorChannel data event notification occurs on the ReactorChannel's specific selectableChannel, as detailed in Section 6.3.
userSpecObj	A pointer that can be set by the user of the Reactor . This value can be set directly or via the creation options. This information can be useful for identifying a specific instance of a Reactor or coupling this Reactor with other user-defined information.

Table 5: Reactor Class Members

6.2.1 Creating a Reactor

The lifecycle of a **Reactor** is controlled by the application, which controls creation and destruction of each reactor instance. The following sections describe creation functionality in more detail.

6.2.1.1 Reactor Creation

The creation of a **Reactor** instance can be accomplished through the use of the following method.

FUNCTION NAME	DESCRIPTION
ReactorFactory.createReactor	Creates a Reactor instance, including all necessary internal memory and threads. After creating the Reactor , ReactorChannels can be associated, as described in Section 6.3. Options are passed in via the ReactorOptions , as defined in Section 6.2.1.2.

Table 6: Reactor Creation Method

6.2.1.2 ReactorOptions Class Members

CLASS MEMBER	DESCRIPTION
enableXmlTracing	Enables XML tracing for the Reactor . The Reactor prints the XML representation of all OMM messages when enabled.
reissueTokenAttemptInterval	The time (in milliseconds) that the Reactor waits before attempting to reissue the token. The minimum interval is 1000 milliseconds, while the default setting is 5000.
reissueTokenAttemptLimit	The maximum number of times the Reactor attempts to reissue the token. If set to default (i.e., -1), there is no maximum limit.
restProxyOptions	Options used for REST requests such as service discovery and to obtain an authentication token.
restRequestTimeOut	Specifies the timeout (in seconds) for token service and service discovery request. If the request times out, the Enterprise Transport API Reactor resends the token reissue and the timeout restarts. When using the Reactor.connect method, if the request times out, the Reactor does not retry. If set to 0, there is no timeout. Be default, the Enterprise Transport API behaves as if set to 45000 milliseconds.

Table 7: ReactorOptions Class Members

CLASS MEMBER	DESCRIPTION
serviceDiscoveryURL	Specifies the URL of Refinitiv Data Platform that the RTSDK API uses to discover service information such as the host and port to which the API connects to retrieve real-time data from the Refinitiv Real-Time solution/offering.
tokenReissueRatio	Specifies a ratio to multiply the access token's expiration time (in seconds) to determine the length of time the Reactor waits before retrieving a new access token and refreshing its connection to Refinitiv Real-Time - Optimized. The valid range is from 0 .05 to 0 .95 . By default, the Enterprise Transport API behaves as if set to 0 .8 .
tokenServiceURL	Specifies the URL of Refinitiv Data Platform that the RTSDK API uses to obtain an authentication token.
userSpecObj	An object that can be set by the application. This value is preserved and stored in the userSpecObj of the Reactor returned from ReactorFactory.createReactor . This information can be useful for identifying a specific instance of a reactor or coupling this Reactor with other user-created information.

Table 7: ReactorOptions Class Members(Continued)**6.2.1.3 ReactorOptions Utility Method**

The Enterprise Transport API provides the following utility method for use with the **ReactorOptions**.

METHOD NAME	DESCRIPTION
clear	Clears the ReactorOptions class. Useful for object reuse.

Table 8: ReactorOptions Utility Method**6.2.1.4 ReactorRestProxyOptions Interface**

The **ReactorRestProxyOptions** interface provides methods that set proxy options for the Reactor to be used for service discovery and authentication.

METHOD	DESCRIPTION
proxyDomain	Specifies the proxy domain of the user to authenticate. Required for NTLM or for Negotiate/Kerberos or for Kerberos authentication protocols.
proxyHostName	Specifies the address or hostname of the HTTP proxy server.
proxyKrb5ConfigFile	Specifies the complete path of the Kerberos5 configuration file (krb5.ini or krb5.conf , or custom file). Needed to Negotiate/Kerberos and Kerberos authentications for the proxy connection.
proxyLocalHostName	Specifies the proxy local hostname. Needed for NTLM authentication protocol only.
proxyPassword	Sets the proxy password to authenticate.
proxyPort	Specifies the port number of the HTTP proxy server.
proxyUserName	Sets the proxy user name to authenticate.

Table 9: ReactorRestProxyOptions Members

6.2.1.5 ReactorDebuggerOptions Interface

The **ReactorDebuggerOptions** interface provides methods that set debugging levels for the Reactor and the output stream for the debugging information.

The debugging levels available for the Reactor are provided in the **ReactorDebuggerLevels** class.

DEBUGGING LEVEL	DESCRIPTION
LEVEL_NONE	No debugging information is logged.
LEVEL_CONNECTION	Provides debugging points for connection events such as CHANNEL_UP , CHANNEL_DOWN , etc.
LEVEL_EVENTQUEUE	Allows obtaining information about the number of events in the Reactor queue and the number of events to be dispatched.
LEVEL_TUNNELSTREAM	Provides debugging points for TunnelStream events.

Table 10: Reactor Debugging Levels

By default, the output is directed to **ByteArrayOutputStream** with a default capacity of 64 KB.

If this limit is exceeded, debugging messages are no longer written into the buffer until the user requests the already logged information. In this case the buffer is cleared and more information can be logged.

For additional information, see Section 6.2.1.6 and Section 6.11.4.

6.2.1.6 ReactorDebuggerOptions Methods

METHOD	DESCRIPTION
setDebuggingLevels(int val)	Sets the levels to be debugged in batch.
enableLevel(int val)	Specifies the debugging level that should be enabled.
disableLevel(int val)	Specifies the debugging level that should be disabled.
debugEnabled()	Determines whether at least one connection level is enabled.
outputStream(OutputStream stream)	Sets the stream into which the information is written.
capacity(int capacity)	Specifies the capacity that should be applied to the output stream if applicable.
clear()	Clears current ReactorDebuggerOptions instance.

6.2.2 Destroying a Reactor

The lifecycle of a **Reactor** instance is controlled by the application, which controls creation and destruction of each reactor instance. The following sections describe the destruction functionality in more detail.

6.2.2.1 Reactor Destruction

When the application no longer requires a **Reactor** instance, it can shutdown it using the following method.

METHOD NAME	DESCRIPTION
shutdown	Shuts down and cleans up a Reactor . This also sends ReactorChannelEvents , indicating channel down, to all ReactorChannels associated with this Reactor .

Table 11: Reactor Destruction Method**6.2.2.2 Reactor Creation and Destruction Example**

```

ReactorOptions reactorCreateOptions = ReactorFactory.createReactorOptions();

reactorCreateOptions.clear();

/* Create the Reactor. */
reactor = ReactorFactory.createReactor(reactorCreateOptions, errorInfo);

/* Any use of the reactor occurs here -- see following sections for all other functionality */

/* Destroy the Reactor. */
reactor.shutdown(errorInfo);

```

Code Example 1: Reactor Creation and Destruction Example**6.3 Reactor Channel Use**

The **ReactorChannel** class is used to represent a connection that can send or receive information across a network. This class is used to represent a connection, regardless of whether it is an outbound connection or a connection accepted by a listening socket via a **Server** instance. The **ReactorChannel** is the application's point of access, used to perform any action on the connection that it represents (e.g., dispatching events, writing, disconnecting, etc.). See the subsequent sections for more information about **ReactorChannel** and how to associate with a **Reactor**.

NOTE: Only Enterprise Transport API Reactor methods, like those defined in this chapter, should be called on a channel managed by a **Reactor**.

The following table describes the members of the **ReactorChannel** class.

CLASS MEMBER	DESCRIPTION
hostname	Provides the name of the host to which a consumer or NIP application connects.
majorVersion	When a ReactorChannel is up (ReactorChannelEventTypes.CHANNEL_UP), this is populated with the major version number associated with the content sent on this connection. Typically only minor version increases are associated with a fully backward compatible change or extension. The Enterprise Transport API Reactor will leverage the versioning information for any content it is encoding or decoding. Proper use of versioning should be handled by the application for any other application encoded or decoded content. For more information on versioning, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 12: Reactorchannel Class Members

CLASS MEMBER	DESCRIPTION
minorVersion	When a ReactorChannel is up (ReactorChannelEventTypes.CHANNEL_UP), this is populated with the minor version number associated with the content sent on this connection. Typically, a minor version increase is associated with a fully backward compatible change or extension. The Enterprise Transport API Reactor will leverage the versioning information for any content it is encoding or decoding. Proper use of versioning should be handled by the application for any other application encoded or decoded content. For more information on versioning, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
oldSelectableChannel	It is possible for a selectable channel to change over time, typically due to some kind of connection keep-alive mechanism. If this occurs, this is typically communicated via a callback indicating ReactorChannelEventTypes.FD_CHANGE . The previous selectable channel is stored in oldSelectableChannel so the application can properly handle the change.
port	Provides the server port number to which the consumer or NIP application connects.
protocolType	When a ReactorChannel is up (ReactorChannelEventTypes.CHANNEL_UP), this is populated with the protocolType associated with the content being sent on this connection. If the server indicates a protocolType that does not match the protocolType specified by the client, the connection is rejected. The Enterprise Transport API Reactor will leverage the versioning information for any content it is encoding or decoding. Proper use of versioning should be handled by the application for any other application encoded or decoded content. For more information on versioning, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
channel	The underlying Channel object, as defined in the Enterprise Transport API Java Edition <i>Developers Guide</i> , mainly for reference purposes. All operations should be performed using the Enterprise Transport API Reactor functionality; the application should not use this Channel directly with any Transport functionality.
server	The underlying Server object, as defined in the Enterprise Transport API Java Edition <i>Developers Guide</i> , mainly for reference purposes. This is populated only if the channel was created via the Reactor.accept method, as described in Section 6.4.1.6.
selectableChannel	Represents a selectable channel that can be used in select notification to alert users when dispatch is required on a specific ReactorChannel . Used to register with a selector.
state	The state of the ReactorChannel .
userSpecObj	An object that can be set by the user of the Channel . This value can be set via the ReactorConnectOption and ReactorAcceptOption . This information can be useful for coupling this ReactorChannel with other user-created information.

Table 12: **ReactorChannel** Class Members (Continued)

6.3.1 Reactor Channel Roles

A **ReactorChannel** can be configured to fulfill several specific roles, which overlap with the typical OMM application types. Provided role definitions include:

- **ConsumerRole** for OMM consumer applications
- **ProviderRole** for OMM interactive provider applications
- **NIPProviderRole** for OMM non-interactive provider applications

All roles have the same base class, **ReactorRole**.

6.3.1.1 ReactorRole Class

ReactorRole contains information and callback methods common to all role types and consists of the following members:

CLASS PROPERTY	DESCRIPTION
channelEventCallback	This ReactorChannel 's user-defined callback method to handle all ReactorChannel specific events, like ReactorChannelEventType.CHANNEL_UP or ReactorChannelEventType.CHANNEL_DOWN . This callback method is required for all role types. This callback is defined in more detail in Section 6.6.2.
defaultMsgCallback	This ReactorChannel 's user-defined callback method to handle Msg content not handled by another domain-specific callback method. This callback method is required for all role types and is defined in more detail in Section 6.6.2.
type	The role type enumeration value, as defined in Section 6.3.1.2.

Table 13: **ReactorRole** Class Members

6.3.1.2 ReactorRoleType Enumerations

ENUMERATED NAME	DESCRIPTION
CONSUMER	Indicates that the ReactorChannel should act as a consumer.
NIPROVIDER	Indicates that the ReactorChannel should act as a non-interactive provider.
PROVIDER	Indicates that the ReactorChannel should act as an interactive provider.

Table 14: **ReactorRoleTypeEnum** Values

6.3.2 Reactor Channel Role: OMM Consumer

When a **ReactorChannel** is acting as an OMM consumer application, it connects to an OMM interactive provider. As part of this process it is expected to perform a login to the system. After the login is completed, the consumer acquires a source directory, which provides information about the available services and their capabilities. Additionally, a consumer can download or load field dictionaries, providing information to help decode some types of content. The messages that are exchanged during this connection establishment process are administrative RDMs and are described in the *Enterprise Transport API Java Edition Refinitiv Domain Model Usage Guide*.

A **ReactorChannel** in a consumer role helps to simplify this connection process by exchanging these messages on the user's behalf. The user can choose to provide specific information or leverage a default populated message, which uses the information of the user currently logged into the machine running the application. In addition, the ETA Reactor allows the application to specify user-defined callback methods to handle the processing of received messages on a per-domain basis.

6.3.2.1 OMM Consumer Role

When creating a **ReactorChannel**, this information can be specified with the **ConsumerRole** object as follows:

CLASS MEMBER PROPERTY	DESCRIPTION
clientId	This member has been deprecated. Instead, use the reactorOAuthCredential member to set all Refinitiv Data Platform token service request credentials.
dictionaryDownloadMode	Informs the ReactorChannel of the method to use when requesting dictionaries. Allowable modes are defined in Section 6.3.2.2.
dictionaryMsgCallback	This ReactorChannel 's user-defined callback method to handle dictionary message content. If not specified, all received dictionary messages will be passed to the defaultMsgCallback . <ul style="list-style-type: none"> For more details on this callback, refer to Section 6.6.2. Dictionary messages are described in Section 8.5.
directoryMsgCallback	This ReactorChannel 's user-defined callback method to handle directory message content. If not specified, all received directory messages will be passed to the defaultMsgCallback . <ul style="list-style-type: none"> For more details on this callback, refer to Section 6.6.2. Directory messages are described in Section 8.4.
loginMsgCallback	This ReactorChannel 's user-defined callback method to handle login message content. If not specified, all received login messages will be passed to the defaultMsgCallback . <ul style="list-style-type: none"> For more details on this callback, refer to Section 6.6.2. Login messages are described in Section 8.3.
rdmDirectoryRequest	The DirectoryRequest (defined in Section 8.4.1) sent during the connection establishment process. This can be populated with specific source directory request information or invoke the initDefaultRDMDirectoryRequest method to populate with default information. <ul style="list-style-type: none"> If this parameter is specified, an DirectoryRequest is required. If this parameter is empty, a directory request is not sent to the system.
reactorOAuthCredential	Specifies the credentials for an application that makes a Refinitiv Data Platform token service request. This is required when connecting to a Refinitiv Real-Time Advanced Distribution Server in the cloud. See Section 6.9.2.1.
rdmLoginRequest	The LoginRequest (defined in Section 8.3.1) sent during the connection establishment process. This can be populated with a user's specific information or invoke the initDefaultRDMLoginRequest method to populate with default information. If this parameter is empty, a login is not sent to the system; useful for systems that do not require a login.

Table 15: ConsumerRole Class Members

6.3.2.2 OMM Consumer Role Dictionary Download Modes

There are several dictionary download options available to a **ReactorChannel**. The application can determine which option is desired and specify using the **ConsumerRole.dictionaryDownloadMode** parameter.

ENUMERATED NAME	DESCRIPTION
FIRST_AVAILABLE	The Reactor will search received directory messages for the RDMFieldDictionary (RWFFId) and the enumtype.def (RWFEnum) dictionaries. Once found, the Reactor will request these dictionaries for the application. After transmission is completed, the streams are closed because this content does not update.
NONE	The Reactor will not request dictionaries for this ReactorChannel . This is typically used when the application has loaded a file-based dictionary or has acquired the dictionary elsewhere.

Table 16: **ConsumerRole.dictionaryDownloadMode** Enumerated Values

6.3.2.3 OMM Consumer Role Watchlist Options

The consumer may enable an internal watchlist and configure behaviors. For more detail on the consumer watchlist feature, refer to Section 2.4.

OPTION	DESCRIPTION
enableWatchlist	Enables the watchlist.
itemCountHint	Can improve performance when used with the watchlist. If possible, set this to the approximate number of item requests the application expects to open.
maxOutstandingPosts	Sets the maximum allowable number of on-stream posts waiting for acknowledgment before the reactor disconnects.
obeyOpenWindow	Sets whether the Reactor obeys the OpenWindow of services advertised in a provider's Source Directory response.
postAckTimeout	Sets the time (in milliseconds) a stream waits to receive an ACK for an outstanding post before forwarding a negative acknowledgment AckMsg to the application.
requestTimeout	Sets the time (in milliseconds) the watchlist waits for a response to a request.

Table 17: OMM Consumer Role Watchlist Options

6.3.2.4 OMM Consumer Role Utility Method

The Enterprise Transport API provides the following utility method for use with the **ConsumerRole**.

METHOD NAME	DESCRIPTION
clear	Clears the ConsumerRole object. Useful for object reuse.

Table 18: **ConsumerRole** Utility Method

6.3.3 Reactor Channel Role: OMM Provider

When a **ReactorChannel** is acting as an OMM provider application, it allows connections from OMM consumer applications. As part of this process it is expected to respond to login requests and source directory information requests. Additionally, a provider can optionally allow consumers to download field dictionaries. Messages exchanged during this connection establishment process are administrative RDMs and are described in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

A **ReactorChannel** in an interactive provider role allows the application to specify user-defined callback methods to handle the processing of received messages on a per-domain basis.

6.3.3.1 OMM Provider Role

When creating a **ReactorChannel**, this information can be specified with the **ProviderRole** class, as follows:

STRUCTURE MEMBER	DESCRIPTION
dictionaryMsgCallback	This ReactorChannel 's user-defined callback method to handle dictionary message content. If unspecified, all received dictionary messages will be passed to the defaultMsgCallback . <ul style="list-style-type: none"> • For further details on this callback, refer to Section 6.6.2. • Dictionary messages are described in Section 8.5.
directoryMsgCallback	This ReactorChannel 's user-defined callback method to handle directory message content. If unspecified, all received directory messages will be passed to the defaultMsgCallback . <ul style="list-style-type: none"> • For further details on this callback, refer to Section 6.6.2. • Directory messages are described in Section 8.4.
loginMsgCallback	This ReactorChannel 's user-defined callback method to handle login message content. If unspecified, all received login messages are passed to the defaultMsgCallback . <ul style="list-style-type: none"> • For further details on this callback, refer to Section 6.6.2. • Login messages are described in Section 8.3.

Table 19: **ProviderRole** Structure Members

6.3.3.2 OMM Provider Role Utility Method

The Enterprise Transport API provides the following utility method for use with the **ProviderRole**.

METHOD NAME	DESCRIPTION
clear	Clears the ProviderRole object. Useful for object reuse.

Table 20: **ProviderRole** Utility Method

6.3.4 Reactor Channel Role: OMM Non-Interactive Provider

When a **ReactorChannel** acts as an OMM non-interactive provider application, it connects to a Refinitiv Real-Time Advanced Data Hub and logs into the system. After login, the non-interactive provider publishes a source directory, which provides information about the available services and their capabilities. Messages exchanged while establishing the connection are administrative RDMs and are described in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*

A **ReactorChannel** in a non-interactive provider role helps to simplify this connection process by exchanging these messages on the user's behalf. The user can choose to provide specific information or leverage a default populated message, which uses the information of the user currently logged into the machine running the application. In addition, the ETA Reactor allows the application to specify user-defined callback functions to handle the processing of received messages on a per-domain basis.

6.3.4.1 OMM Non-Interactive Role Members

When creating a **ReactorChannel**, this information can be specified with the **NIPrviderRole** class, as follows:

PROPERTY	DESCRIPTION
rdmLoginRequest	The LoginRequest , defined in Section 8.3.1, sent when establishing a connection. You can populate this with a user's specific information or invoke the initDefaultRDMLoginRequest method to populate with a default set of information. If empty, a login is not sent to the system; useful for systems that do not require a login.
rdmDirectoryRefresh	The DirectoryRefresh , defined in Section 8.4.2, sent when establishing a connection. You can populate this with specific source directory refresh information or invoke the initDefaultRDMDirectoryRefresh method to populate it with default information. <ul style="list-style-type: none"> • If this parameter is specified, an rdmDirectoryRefresh is required. • If this parameter is left empty, a refresh is not automatically sent to the system.
loginMsgCallback	The ReactorChannel 's user-defined callback method that handles login message content. If unspecified, all received login messages are passed to the defaultMsgCallback . For further details on this callback, refer to Section 6.6.2.

Table 21: **NIPrviderRole** Class Members

6.3.4.2 OMM Non-Interactive Provider Role Utility Method

The Enterprise Transport API provides the following utility method for use with the **NIPrviderRole**.

FUNCTION NAME	DESCRIPTION
clear	Clears the NIPrviderRole object. Useful for object reuse.

Table 22: **NIPrviderRole** Utility Method

6.4 Managing Reactor Channels

6.4.1 Adding Reactor Channels

A single **Reactor** instance can manage multiple **ReactorChannels**. A **ReactorChannel** can be instantiated as an outbound client style connection or as a connection that is accepted from a **Server**. Thus, users can mix connection styles within or across Reactors and have consistent usage and behavior.

NOTE: A single **Reactor** can simultaneously manage **ReactorChannels** from **Reactor.connect** and **Reactor.accept**.

6.4.1.1 Reactor Connect

The **ReactorConnect** method will create a new **ReactorChannel** and associate it with a **Reactor**. This method creates a new outbound connection. The **ReactorChannel** is returned to the application via a callback, as described in Section 6.6.2, at which point it begins dispatching.

Client applications can specify that **Reactor** automatically reconnect a **ReactorChannel** whenever a connection fails. To enable this, the application sets the appropriate members of the **ReactorConnectOption** object. The application can specify that **Reactor** reconnect the **ReactorChannel** to the same host, or to one from among multiple hosts.

METHOD NAME	DESCRIPTION
ReactorConnect	<p>Creates a ReactorChannel that makes an outbound connection to the configured host. This establishes a connection in a manner similar to the Connect method, as described in the Enterprise Transport API Java Edition <i>Developers Guide</i>. Connection options are passed in via the ReactorConnectOption, as defined in Section 6.4.1.2.</p> <p>ReactorChannel specific information, such as the per-channel callback functions, the type of behavior, default RDM messages, and such are passed in via the ReactorRole, as defined in Section 6.3.1.</p>

Table 23: **ReactorConnect** Method

6.4.1.2 ReactorConnectOptions Class Members

CLASS MEMBER	DESCRIPTION
connectionList	Specifies ReactorConnectInfo as defined in Section 6.4.1.3. When used with reconnectAttemptLimit , the Reactor attempts to connect to each host in the list with each reconnection attempt.
reconnectAttemptLimit	The maximum number of times the Reactor attempts to reconnect a channel when it fails. If set to -1 , there is no limit.
reconnectMinDelay	Specifies the minimum length of time the Reactor waits (in milliseconds) before attempting to reconnect a failed channel. The time increases with each reconnection attempt, from reconnectMinDelay to reconnectMaxDelay .

Table 24: **ReactorConnectOptions** Structure Members

CLASS MEMBER	DESCRIPTION
reconnectMaxDelay	Specifies the maximum length of time the Reactor waits (in milliseconds) before attempting to reconnect a failed channel. The time increases with each reconnection attempt, from reconnectMinDelay to reconnectMaxDelay .
	NOTE: The proxy settings specified in connectOptions can be used to invoke REST requests such as service discovery and obtain an authentication token. They have lower precedence than the proxy settings specified in RsslCreateReactorOptions.restProxyOptions . For further details, refer to Section 6.2.1.2.
statisticFlags	Specifies ReactorChannelStatisticFlags which set the type of statistics reporting (if any) to perform on the Reactor channel. ReactorChannelStatisticFlags uses the following enums: <ul style="list-style-type: none"> • RSSL_RC_ST_NONE (or 0x0000): Turns off statistics reporting. • RSSL_RC_ST_READ (or 0x0001): Turns on statistics reporting for the number of bytes read and the number of uncompressed bytes read. • RSSL_RC_ST_WRITE (or 0x0002): Turns on statistics reporting for the number of bytes written and uncompressed bytes written. • RSSL_RC_ST_PING (or 0x0004): Turns on statistics reporting for the number of pings received and the number of pings sent.

Table 24: ReactorConnectOptions Structure Members (Continued)

6.4.1.3 ReactorConnectInfo Class Members

CLASS MEMBER	DESCRIPTION
connectOptions	Specifies information about the host or network to which to connect, the type of connection to use, and other transport-specific configuration information associated with the underlying Connect method. This is described in more detail in the Enterprise Transport API Java Edition <i>Developers Guide</i> .
enableSessionManagement	Specifies whether the channel manages the authentication token on behalf of the user used to keep the session alive. Boolean. If set to true , the channel obtains the authentication token and refreshes it on behalf of user to keep session active. The default setting is false .
initTimeout	Specifies the amount of time (in seconds) to wait to successfully establish a ReactorChannel . If a ReactorChannel is not established in this timeframe, an event is dispatched to the application to indicate that the ReactorChannel is down.
location	Specifies the cloud location (e.g., us-east-1) of the service provider endpoint to which the RTSDK API establishes a connection. If location is not specified, the default setting is us-east-1 . In any particular cloud location, the Reactor connects to the endpoint that provides two available zones for the location (e.g., [us-east-1a, us-east-1b]).
loginReqIndex	This specifies the login message to be used for this connection, contained in the pointer array of RsslReactorOMMConsumerRole.pLoginRequestList . If RsslReactorOMMConsumerRole.pLoginRequestList is specified, then this connection will use that login message and login credential callback when it connects. This must be less than RsslReactorOMMConsumerRole.pLoginRequestCount . This is a 0 indexed array. For details, see Section 6.5.

Table 25: ReactorConnectInfo Class Members

CLASS MEMBER	DESCRIPTION
oAuthCredentialIndex	This specifies the oAuth credential to be used for this connection, contained in the pointer array of RsslReactorOMMConsumerRole.pOAuthCredentialList , if enableSessionManagement is turned on and RsslReactorOMMConsumerRole.oAuthCredentialCount has been set. This must be less than the number set in RsslReactorOMMConsumerRole.oAuthCredentialCount . This is a 0 indexed array. For details, see Section 6.5.
serviceDiscoveryRetryCount	The number of times the Reactor attempts to reconnect a channel before forcing the API to retry service discovery. See the description of ReactorOptions.serviceDiscoveryURL in Section 6.2.1.2. This functionality works when the user sets enableSessionManagement to true, but is ignored when the user sets the values of UnifiedNetworkInfo.address and UnifiedNetworkInfo.serviceName in ConnectOptions directly. For details, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> . The default value is 3. After each 3 attempts to reconnect a channel, the Reactor will force to retry service discovery. The Reactor will not retry to get an endpoint from the service discovery when the value is 0.
reactorAuthTokenEventCallback	A callback function that receives ReactorAuthTokenEvents . The Reactor requests a token for the Consumer and NiProvider applications to send login requests and reissues with the token.

Table 25: ReactorConnectInfo Class Members (Continued)

6.4.1.4 ReactorConnectOptions Utility Method

The Enterprise Transport API provides the following utility function for use with the **ReactorConnectOptions**.

FUNCTION NAME	DESCRIPTION
clear	Clears the ReactorConnectOptions object. Useful for object reuse.

Table 26: ReactorConnectOptions Utility Method

6.4.1.5 Reactor.connect Example

```

ReactorConnectOptions connectOpts = ReactorFactory.createReactorConnectOptions();
ConsumerRole consumerRole = ReactorFactory.createConsumerRole();

/* Configure connection options.*/
connectOpts.clear();
connectOpts.connectOptions.connectionList().get(0).connectOptions().unifiedNetworkInfo().address
    ("localhost");
connectOpts.connectOptions.connectionList().get(0).connectOptions().unifiedNetworkInfo().serviceName
    ("14002");

/* Configure a role for this connection as an OMM Consumer. */
consumerRole.clear();

/* Set the methods to which dispatch will deliver events. */
consumerRole.channelEventCallback(channelEventCallback);
consumerRole.defaultMsgCallback(defaultMsgCallback);
consumerRole.loginMsgCallback(loginMsgCallback);

```

```
consumerRole.directoryMsgCallback(directoryMsgCallback);
consumerRole.dictionaryMsgCallback(dictionaryMsgCallback);

/* Initialize a default login request. Once the channel is initialized this message will be sent. */
consumerRole.initDefaultRDMLoginRequest();

/* Initialize a default directory request. Once the application has logged in, this message will be
   sent. */
consumerRole.initDefaultRDMDirectoryRequest();

/* Add the connection to the Reactor. */
ret = reactor.connect(connectOpts, consumerRole, errorInfo);
```

Code Example 2: Reactor.connect Example

6.4.1.6 Reactor Accept

The **ReactorAccept** method creates a new **ReactorChannel** and associates it with an **Reactor**. This method accepts the connection from an already running **I Server**. The **ReactorChannel** will be returned to the application via a callback, as described in Section 6.6.2, at which point it can begin dispatching on the channel.

METHOD NAME	DESCRIPTION
ReactorAccept	<p>Creates a ReactorChannel by accepting it from a I Server. This establishes a connection in a manner similar to the Reactor.Accept() function, as described in the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p> <ul style="list-style-type: none"> • Connection options are passed in via ReactorAcceptOptions, as defined in Section 6.4.1.7. • ReactorChannel-specific information (such as the per-channel callback functions, the type of behavior, default RDM messages, and etc.) are passed in via the ReactorRole, as defined in Section 6.3.1.

Table 27: **Reactor.Accept** Function

6.4.1.7 ReactorAcceptOptions Class Members

CLASS MEMBER	DESCRIPTION
AcceptOptions	The AcceptOptions associated with the underlying Accept method. This includes an option to reject the connection as well as a userSpecObj . This is described in more detail in the Enterprise Transport API Java Edition <i>Developers Guide</i> .
initTimeout	The amount of time (in seconds) to wait for the successful connection establishment of a ReactorChannel . If a timeout occurs, an event is dispatched to the application to indicate that the ReactorChannel is down.

Table 28: **ReactorAcceptOptions** Class Members

6.4.1.8 ReactorAcceptOptions Utility Function

The Enterprise Transport API provides the following utility method for use with the **ReactorAcceptOptions**.

METHOD NAME	DESCRIPTION
clear	Clears the ReactorAcceptOptions object. Useful for object reuse.

Table 29: **ReactorAcceptOptions** Utility Method

6.4.1.9 Reactor.accept Example

```

ReactorAcceptOptions reactorAcceptOpts = ReactorFactory.createReactorAcceptOptions();
ProviderRole providerRole = ReactorFactory.createProviderRole();

/* Configure accept options.*/
reactorAcceptOpts.clear();
reactorAcceptOpts.acceptOptions().userSpecObject(server);

/* Configure a role for this connection as an OMM Provider. */
providerRole.clear();
providerRole.channelEventCallback(channelEventCallback);
providerRole.defaultMsgCallback(defaultMsgCallback);
providerRole.loginMsgCallback(loginMsgCallback);
providerRole.directoryMsgCallback(directoryMsgCallback);
providerRole.dictionaryMsgCallback(dictionaryMsgCallback);

/* Add the connection to the Reactor by accepting it from a Server. */
ret = reactor.accept(server, reactorAcceptOpts, providerRole, errorInfo)

```

Code Example 3: Reactor.accept Example

6.4.2 Removing Reactor Channels

6.4.2.1 ReactorChannel.close Method

You use the following method to remove a **ReactorChannel** from a **Reactor** instance. It can also close and clean up resources associated with the **ReactorChannel**.

FUNCTION NAME	DESCRIPTION
ReactorChannel.close	Removes a ReactorChannel from the passed in Reactor associated with the current ReactorChannel instance and cleans up associated resources. This additionally invokes the Channel.close method, as described in the Enterprise Transport API Java Edition <i>Developers Guide</i> , to clean up any resources associated with the underlying Channel . This method can be called from either outside or within a callback.

Table 30: ReactorChannel.close Function

6.4.2.2 ReactorChannel.close Example

```

ReactorErrorInfo errorInfo = ReactorFactory.createReactorErrorInfo();
/* Can be used inside or outside of a callback */
ret = reactorChannel.close(errorInfo);

```

Code Example 4: ReactorChannel.close Example

6.5 Reporting on Channel Statistics

You can use the `ReactorRetrieveChannelStatistic()` method to report on channel statistics. To use this method, you must first activate channel statistics reporting in `RsslReactorConnectOptions` by setting the `statisticFlags` member (for details on this member and the types of statistics on which you can report, refer to Section 6.4.1.2).

To get statistics, create a `ReactorChannelStatistic` structure and pass it in with the method. The Enterprise Transport API responds with the data for which the `statisticFlags` expressed interest.

6.6 Dispatching Data

Once an application has a `Reactor`, it can begin dispatching messages. Until there is at least one associated `ReactorChannel`, there is nothing to dispatch. When `ReactorChannels` are available for dispatching, each channel begins seeing its user-defined per-channel callbacks being invoked. For more information about available callbacks and their specifications, refer to Section 6.6.2.

An application can choose to dispatch across all associated `ReactorChannels` (via `Reactor.dispatchAll`) or on a particular `ReactorChannel` (via `ReactorChannel.dispatch`). If dispatching across multiple `ReactorChannels`, the `Reactor` attempts to fairly dispatch over all channels. In either case, the application can use the dispatch call to specify the maximum number of messages that will be processed and returned via callback.

Typically, an application registers both the `Reactor`'s internal `ReactorChannel`'s `selectableChannel` and each `ReactorChannel`'s `selectableChannel` with an `select` notifier. The `select` notifier can help inform the application when data is available on particular `ReactorChannels` or when channel information is available from the `Reactor` (via its internal `ReactorChannel`). An application can also forgo the use of notifiers and instead periodically call the `dispatch` function to process data as described in Section 6.6.1.

6.6.1 Reactor Dispatch Methods

NOTE: Applications should not call `Reactor.shutdown`, `ReactorChannel.dispatch` or `Reactor.dispatchAll` from within a callback function. All other `Reactor` functionality is safe to use from within a callback.

Events received in callback methods should be assumed to be invalid when the callback method returns. For callbacks that provide `Msg`, `LoginMsg`, `DirectoryMsg`, or `DictionaryMsg` classes, a deep copy of the object should be made if the application wishes to preserve it. To copy a `Msg`, refer to the `Msg.copy` method in the Enterprise Transport API Java Edition *Developers Guide*; for copying a `LoginMsg`, `DirectoryMsg`, or `DictionaryMsg` object, refer to the `copy` utility method for the appropriate RDM message type.

METHOD NAME	DESCRIPTION
<code>ReactorChannel.dispatch</code>	This method processes a specific channel's events and messages from the <code>Reactor</code> . When channel information or data is available for a <code>ReactorChannel</code> , the channel's user-defined callback method is invoked. The application can control the maximum number of messages dispatched with a single call to <code>ReactorChannel.dispatch</code> . This can be controlled through passed-in <code>ReactorDispatchOptions</code> (for details refer to Section 6.6.1.1).

Table 31: `ReactorChannel.dispatch` Method

6.6.1.1 Reactor Dispatch Options

An application can use `ReactorDispatchOptions` to control various aspects of the call to `Reactor.dispatchAll` and `ReactorChannel.dispatch`.

	DESCRIPTION
maxMessages	Controls the maximum number of events or messages processed in this call. If this is larger than the number of available messages, Reactor.dispatchAll or ReactorChannel.dispatch will return when there is no more data to process. This value is initialized to allow up to 100 messages to be returned with a single call to Reactor.dispatchAll or ReactorChannel.dispatch .
readArgs	The ReadArgs from the underlying Channel.read call.

Table 32: ReactorDispatchOptions Members

6.6.1.2 ReactorDispatchOptions Utility Function

The Enterprise Transport API provides the following utility method for use with **ReactorDispatchOptions**.

METHOD NAME	DESCRIPTION
clear Clear	Clears the ReactorDispatchOptions class. Useful for class reuse.

Table 33: ReactorDispatchOptions Utility Method

6.6.1.3 ReactorChannel.dispatch Example

```
ReactorDispatchOptions dispatchOpts = ReactorFactory.createReactorDispatchOptions();

/* Set dispatching options. */
dispatchOpts.clear();
dispatchOpts.maxMessages(200);

/* Call ReactorChannel.dispatch(). It will keep dispatching events until there is nothing to read or
 * maxMessages is reached. */
ret = reactorChannel.dispatch(dispatchOpts, errorInfo);
```

Code Example 5: ReactorChannel.dispatch Example

6.6.2 Reactor Callback Methods

A series of callback methods returns (to the application) any state information about the **ReactorChannel** connection as well as messages for that channel. Each **ReactorChannel** can define its own unique callback methods or specify callback methods that can be shared across channels.

There are several values that can be returned from a callback method implementation. These can trigger specific **Reactor** behaviors based on the outcome of the callback method. Callback return values are as follows:

RETURN CODE	DESCRIPTION
SUCCESS	Indicates that the callback function was successful and the message or event has been handled.
FAILURE	Indicates that the message or event has failed to be handled. Returning this code from any callback function will cause the Reactor to shutdown.
RAISE	Can be returned from any domain-specific callback (e.g., IRDMLoginMsgCallback). This will cause the Reactor to invoke the DefaultMsgCallback for this message upon the domain-specific callbacks return.

Table 34: ReactorCallbackReturnCodes Callback Return Codes

All events communicated to callback methods have the same base class, the **ReactorEvent**, which contains information common to all callback events.

CLASS MEMBER	DESCRIPTION
reactorChannel	The ReactorChannel on which the event occurred.
errorInfo	The ReactorErrorInfo associated with this event.

Table 35: ReactorEvent Class Members

6.6.3 Reactor Callback: Channel Event

The **Reactor** channel event callback communicates **ReactorChannel** and connection state information to the application. This interface has the following callback method:

```
reactorChannelEventCallback(ReactorChannelEvent event)
```

When invoked, this returns a **ReactorChannelEvent** class, containing more information about the event.

6.6.3.1 Reactor Channel Event

The **ReactorChannelEvent** is returned to the application via the **reactorChannelEventCallback**.

MEMBER	DESCRIPTION
eventType	The type of event that has occurred on the ReactorChannel . For a list of enumeration values, refer to Section 6.6.3.2.

Table 36: ReactorChannelEvent

6.6.3.2 Reactor Channel Event Type Enumeration Values

FLAG ENUMERATION	MEANING
CHANNEL_DOWN	Indicates that the ReactorChannel is not available for use. This could be a result of an initialization failure, a ping timeout, or some other kind of connection-related issue. ReactorErrorInfo will contain more detailed information about what occurred. There is no connection recovery for this event. To clean up the failed ReactorChannel , the application should call ReactorChannel.close .
CHANNEL_DOWN_RECONNECTING	Indicates that the ReactorChannel is temporarily unavailable for use. The Reactor will attempt to reconnect the channel according to the values specified in ReactorConnectOptions when Reactor.connect was called. This only occurs on client connections because there is no connection recovery for server connections. If the watchlist is enabled, requests are recovered as appropriate when the channel successfully reconnects. Before exiting the channelEventCallback , the application should release any resources associated with the channel, such as TransportBuffers , and unregister its selectableChannel , if valid, from any select notifiers.
CHANNEL_OPENED	Indicates that the watchlist is enabled and that a channel has been created via Reactor.connect . Though the channel is still not ready for dispatch, the application can begin submitting request messages, which are sent after the channel successfully initializes.
CHANNEL_READY	Indicates that the ReactorChannel has successfully completed any necessary initialization processes. Where applicable, this includes exchanging any provided Login, Directory, or Dictionary content. The application should now be able to consume or provide content.
CHANNEL_UP	Indicates that the ReactorChannel is successfully initialized and available for dispatching. Where applicable, any specified Login, Directory, or Dictionary messages are exchanged by the Reactor .
FD_CHANGE	Indicates that a selectable channel change occurred on the ReactorChannel . If the application is using an select notification mechanism, unregister the oldSelectableChannel oldSelectableChannel and register the selectableChannel , both of which can be found on the ReactorChannel .
INIT	Channel event initialization value. This should not be used by nor returned to the application.
WARNING	Indicates that the ReactorChannel has experienced an event that did not result in connection failure, but may require the attention of the application. ReactorErrorInfo contains more detailed information about what occurred.

Table 37: **ReactorChannelEventType** Enumeration Values

6.6.3.3 Reactor Channel Event Utility Methods

METHOD NAME	DESCRIPTION
clearClear	Clears a ReactorChannelEvent class.

Table 38: **ReactorChannelEvent** Utility Methods

6.6.3.4 Reactor Channel Event Callback Example

```

public int reactorChannelEventCallback(ReactorChannelEvent event)
{
    switch(event.eventType())
    {
        case ReactorChannelEventTypes.CHANNEL_UP:
            // register selector with channel event's reactorChannel
            event.reactorChannel().selectableChannel().register(selector, SelectionKey.OP_READ,
                event.reactorChannel());
            break;

        case ReactorChannelEventTypes.CHANNEL_DOWN:
            // close ReactorChannel
            if (event.reactorChannel() != null)
            {
                event.reactorChannel().close(errorInfo);
            }
            break;

        case ReactorChannelEventTypes.CHANNEL_READY:
            /* Channel has exchanged its initial messages (if any were provided on the role object)
             * and is ready for use. */
            sendItemRequests(reactorChannel);
            break;

        case ReactorChannelEventTypes.FD_CHANGE:
            /* The descriptor representing this channel has changed. Normally the application only
             * needs to update its notification mechanism in response to this event. */
            // cancel old reactorChannel select
            SelectionKey key = event.reactorChannel().oldSelectableChannel().keyFor(selector);
            key.cancel();
            // register selector with channel event's new reactorChannel
            event.reactorChannel().selectableChannel().register(selector, SelectionKey.OP_READ,
                event.reactorChannel());
            break;

    }
    return ReactorCallbackReturnCodes.SUCCESS;
}

```

Code Example 6: Reactor Channel Event Callback Example

6.6.4 Reactor Callback: Default Message

The **Reactor** default message callback communicates all received content that is not handled directly by a domain-specific callback method. This callback is also invoked after any domain-specific callback that returns the **ReactorCallbackReturnCodes.RAISE** value. This interface has the following callback method:

```
public int defaultMsgCallback(ReactorMsgEvent event)
```

When invoked, this returns a **ReactorMsgEvent** object, containing more information about the event information.

6.6.4.1 Reactor Message Event

The **ReactorMsgEvent** is returned to the application via the **DefaultMsgCallback**. This is also the base class of the **RDMDictionaryMsgEvent**, **RDMDirectoryMsgEvent**, and **LoginMsg** classes.

CLASS MEMBER	DESCRIPTION
transportBuffer	A TransportBuffer containing the raw, undecoded message that was read and processed by the callback. NOTE: When the consumer watchlist is enabled, a TransportBuffer is not provided, because the message might not match this buffer, or the message might be internally generated.
msg	A Msg object populated with message content by calling the Msg.decode . If not present, an error was encountered while processing the information. NOTE: When the consumer watchlist is enabled, msg is not provided to callback functions that provide RDM messages.
streamInfo	Any information associated with a stream (only when the consumer watchlist is enabled).

Table 39: **ReactorMsgEvent** Class Members

6.6.4.2 Reactor Message Event Utility Methods

METHOD NAME	DESCRIPTION
clear	Clears a ReactorMsgEvent object.

Table 40: **ReactorMsgEvent** Utility Method

6.6.4.3 Reactor Message Event Callback Example

```
public int defaultMsgCallback(ReactorMsgEvent event)
{
    Msg msg = event.msg();

    /* Received a Msg --- or, if the decode failed, an error. */
    /* The Msg will have already been passed through Msg.decode. Only the payload requires
       additional decoding. */
    if (msg != null)
        processMsg(msg);
    else
        System.out.printf("defaultMsgCallback Error: %s(%s)\n",
                           event.errorInfo().error().text(),
                           event.errorInfo().location());
}
```

Code Example 7: Reactor Message Event Callback Example

6.6.5 Reactor Callback: RDM Login Message

The **Reactor** RDM Login Message callback is used to communicate all received RDM Login messages. This interface has the following callback method:

```
public int rdmLoginMsgCallback(RDMLoginMsgEvent event)
```

When invoked, this will return the **RDMLoginMsgEvent** object, containing more information about the event information.

6.6.5.1 Reactor RDM Login Message Event

The **RDMLoginMsgEvent** is returned to the application via the **RDMLoginMsgCallback**.

CLASS MEMBER	DESCRIPTION
rdmLoginMsgLoginMsg	The RDM representation of the decoded Login message. If not present, an error was encountered while processing the information. This message is presented as the LoginMsg , described in Section 8.3.

Table 41: RDMLoginMsgEvent Member

6.6.5.2 Reactor RDM Login Message Event Utility Method

METHOD NAME	DESCRIPTION
clear	Clears a RDMLoginMsgEvent object.

Table 42: RDMLoginMsgEvent Utility Method

6.6.5.3 Reactor RDM Login Message Event Callback Example

```

public int rdmLoginMsgCallback(RDMLoginMsgEvent event)
{
    LoginMsg loginMsg = event.rdmLoginMsg();

    /* Received an RDM LoginMsg --- or, if the decode failed, an error. */
    /* The login message will already be fully decoded. */
    if (loginMsg != null)
    {
        switch(loginMsg.rdmMsgType())
        {
            case REFRESH:
                LoginRefresh refresh = (LoginRefresh)loginMsg;
                break;
            case STATUS:
                LoginStatus status = (LoginStatus)loginMsg;
                break;
            default:
                System.out.println("Received unhandled login message.");
                break;
        }
    }
    else
        System.out.printf("rdmLoginMsgCallback Error: %s(%s)\n",
                          event.errorInfo().error().text(),
                          event.errorInfo().location());
}

```

Code Example 8: Reactor RDM Login Message Event Callback Example

6.6.6 Reactor Callback: RDM Directory Message

The **Reactor** RDM Directory Message callback is used to communicate all received RDM Directory messages. This interface has the following callback method:

```
public int rdmDirectoryMsgCallback(RDMDirectoryMsgEvent event)
```

When invoked, this will return the **RDMDirectoryMsgEvent** object, containing more information about the event information.

6.6.6.1 Reactor RDM Directory Message Event

The **RDMDirectoryMsgEvent** is returned to the application via the **RDMDirectoryMsgCallback**.

CLASS MEMBER	DESCRIPTION
rdmDirectoryMsg	<p>The RDM representation of the decoded Source Directory message. If not present, an error was encountered while processing the information.</p> <p>This message is presented as the DirectoryMsg, described in Section 8.4.</p>

Table 43: RDMDirectoryMsgEvent Class Member

6.6.6.2 Reactor RDM Directory Message Event Utility Method

METHOD NAME	DESCRIPTION
clear	Clears an RDMDirectoryMsgEvent object.

Table 44: RDMDirectoryMsgEvent Utility Method

6.6.6.3 Reactor RDM Directory Message Event Callback Example

```

public int rdmDirectoryMsgCallback(RDMDirectoryMsgEvent event)
{
    DirectoryMsg directoryMsg = event.rdmDirectoryMsg();

    /* Received an RDM DirectoryMsg --- or, if the decode failed, an error. */
    /* The directory message will already be fully decoded. */
    if (directoryMsg != null)
    {
        switch(directoryMsg.rdmMsgType())
        {
            case REFRESH:
                DirectoryRefresh refresh = (DirectoryRefresh)directoryMsg;
                break;
            case UPDATE:
                DirectoryUpdate update = (DirectoryUpdate)directoryMsg;
                break;
            case STATUS:
                DirectoryStatus status = (DirectoryStatus)directoryMsg;
                break;
            default:
                System.out.println("Received unhandled directory message.");
        }
    }
    else
        System.out.printf("rdmDirectoryMsgCallback Error: %s(%s)\n",
                           event.errorInfo().error().text(),
                           event.errorInfo().location());
}

```

Code Example 9: Reactor RDM Directory Message Event Callback Example

6.6.7 Reactor Callback: RDM Dictionary Message

The **Reactor** RDM Dictionary Message callback is used to communicate all received RDM Dictionary messages. This interface has the following callback method:

```
public int rdmDictionaryMsgCallback(RDMDictionaryMsgEvent event)
```

When invoked, this will return the **RDMDictionaryMsgEvent** object, containing more information about the event information.

6.6.7.1 Reactor RDM Dictionary Message Event

The **RDMDictionaryMsgEvent** is returned to the application via the **RDMDictionaryMsgCallback**.

CLASS MEMBER	DESCRIPTION
rdmDictionaryMsg	The RDM representation of the decoded Dictionary message. If not present, an error was encountered while processing the information. This message is presented as the DictionaryMsg , described in Section 8.5.

Table 45: RDMDictionaryMsgEvent Class Member

6.6.7.2 Reactor RDM Dictionary Message Event Utility Method

METHOD NAME	DESCRIPTION
clear	Clears an RDMDictionaryMsgEvent object.

Table 46: RDMDictionaryMsgEvent Utility Method

6.6.7.3 Reactor RDM Dictionary Message Event Callback Example

```
public int rdmDictionaryMsgCallback(RDMDictionaryMsgEvent event)
{
    DictionaryMsg dictionaryMsg = event.rdmDictionaryMsg();

    /* Received an RDM DictionaryMsg --- or, if the decode failed, an error. */
    if (dictionaryMsg != null)
    {
        switch(dictionaryMsg.rdmMsgType())
        {
            case REFRESH:
                DictionaryRefresh refresh = (DictionaryRefresh)dictionaryMsg;
                break;
            case STATUS:
                DictionaryStatus status = (DictionaryStatus)dictionaryMsg;
                break;
            default:
                System.out.println("Received unhandled dictionary message.");
        }
    }
}
```

```

    }
else
    System.out.printf("rdmDictionaryMsgCallback Error: %s(%s)\n",
        event.errorInfo().error().text(),
        event.errorInfo().location());
}

```

Code Example 10: Reactor RDM Dictionary Message Event Callback Example

6.7 Writing Data

The Enterprise Transport API Reactor helps streamline the high performance writing of content. The **Reactor** flushes content to the network so the application does not need to. The **Reactor** does so through the use of a separate worker thread that becomes active whenever there is queued content that needs to be passed to the connection.

The Enterprise Transport API Reactor offers two methods for writing content: **ReactorChannel.submit(Msg...)** and **ReactorChannel.submit(TransportBuffer...)**. When writing applications to the Reactor, consider which is most appropriate for your needs:

ReactorChannel.submit(Msg...)

- Takes an **Msg** object as part of its options; does not require retrieval of an **TransportBuffer** from the channel.
- Must be used when the consumer watchlist is enabled.

ReactorChannel.submit(TransportBuffer...)

- Takes an **TransportBuffer** which the application retrieves from the channel.
- More efficient: the application encodes directly into the buffer, and can use buffer packing.
- Cannot be used when the consumer watchlist is enabled.

6.7.1 Writing Data using ReactorChannel.submit(Msg...)

ReactorChannel.submit provides a simple interface for writing **Msg**s. To send a message, the application populates an **Msg** object, sets any other desired options on a **ReactorSubmitOptions** object, and calls **ReactorChannel.submit(Msg...)** with the object.

A buffer is not needed to use **ReactorChannel.submit(Msg...)**. If the application needs to include any encoded content, it can encode the content into any available memory, and set the appropriate member of the **Msg** to point to the memory (as well as set the length of the encoded content).

6.7.1.1 ReactorChannel.submit(Msg...) Method

METHOD NAME	DESCRIPTION
ReactorChannel.submit	Encodes and submits a Msg to the Reactor. This method expects a properly populated Msg .

Table 47: **ReactorChannel.submit(Msg...)** Method

6.7.1.2 Reactor Submit Options

An application can use **ReactorSubmitOptions** to control various aspects of the call to **ReactorChannel.submit**.

CLASS MEMBER	DESCRIPTION
serviceName	<p>The application can use this instead of the serviceId member specified on the MsgKey of a Msg.</p> <p>When used to open streams via request messages, the Reactor will recover using this service name.</p> <p>When used for other message types such as a post or generic message, the Reactor converts the name to its corresponding ID before writing the message.</p> <p>NOTE: This option is supported only when the watchlist is enabled.</p>
requestMsgOptions	Provides additional functionality that may be used when using request messages to send requests.
writeArgs.bytesWritten	If specified, will return the number of bytes to be written, including any transport header overhead and taking into account any savings from compression.
writeArgs.flags	Flag values that allow the application to modify the behavior of this ReactorChannel.submit call. This includes options to bypass queuing or compression. More information about the specific flag values is available in the Enterprise Transport API Java Edition <i>Developers Guide</i> .
writeArgs.priority	<p>Controls the priority at which the data will be written. Valid priorities are</p> <ul style="list-style-type: none"> • WritePriorities.HIGH • WritePriorities.MEDIUM • WritePriorities.LOW <p>More information about write priorities, including an example scenario, is available in the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>
writeArgs.uncompressedBytesWritten	If specified, will return the number of bytes to be written, including any transport header overhead but not taking into account any compression savings.

Table 48: ReactorSubmitOptions Class Members

6.7.1.3 ReactorChannel.submit(Msg...) Return Codes

The following table defines the return codes that can occur when using **ReactorChannel.submit(Msg...)**.

RETURN CODE	DESCRIPTION
ReactorReturnCodes.SUCCESS	Indicates that the ReactorChannel.submit(Msg...) method has succeeded.
ReactorReturnCodes.NO_BUFFERS	Indicates that not enough pool buffers are available to write the message. The application can try to submit the message later, or it can use ReactorChannel.ioctl to increase the number of available pool buffers and try again.
ReactorReturnCodes.WRITE_CALL AGAIN	Indicates that buffer created for the Msg is being fragmented and needs to be called again with the same Msg . This indicates that underlying write was unable to send all fragments with the current call and must continue fragmenting.
ReactorReturnCodes.FAILURE	Indicates that a general failure has occurred and the message was not submitted. The ReactorErrorInfo object passed to the method will contain more details.

Table 49: Reactorchannel.submit(Msg...) Return Codes

6.7.1.4 ReactorRequestMsgOptions

ReactorRequestMsgOptions provide additional functionality when requesting items. These options are available only when the consumer watchlist is enabled.

CLASS MEMBER	DESCRIPTION
userSpecObj	A user-specified object that will be associated with the stream. This object will be provided in responses to this stream via the WatchlistStreamInfo provided with each message event.

Table 50: ReactorRequestMsgOptions Class Members

6.7.1.5 ReactorSubmitOptions Utility Method

The Enterprise Transport API provides the following utility function for use with **ReactorSubmitOptions**.

METHOD NAME	DESCRIPTION
clear	Clears the ReactorSubmitOptions object. Useful for object reuse.

Table 51: ReactorSubmitOptions Utility Method

6.7.1.6 ReactorChannel.submit(Msg...) Example

The following example shows typical use of `ReactorChannel.submit(Msg...)`.

```
RequestMsg requestMsg = (RequestMsg) CodecFactory.createMsg();
ReactorSubmitOptions opts = ReactorFactory.createReactorSubmitOptions();
ReactorErrorInfo errorInfo = ReactorFactory.createReactorErrorInfo();
int ret;

requestMsg.clear();
requestMsg.msgClass(MsgClasses.REQUEST);
requestMsg.streamId(2);
requestMsg.domainType(DomainTypes.MARKET_PRICE);
requestMsg.containerType(DataTypes.NO_DATA);
requestMsg.applyStreaming();
requestMsg.applyHasQos();
requestMsg.qos().timeliness(QosTimeliness.REALTIME);
requestMsg.qos().rate(QosRates.TICK_BY_TICK);
requestMsg.msgKey().applyHasName();
requestMsg.msgKey().applyHasServiceId();
requestMsg.msgKey().name().data("TRI.N");
requestMsg.msgKey().serviceId(1);

ret = reactorChannel.submit(requestMsg, opts, errorInfo);
```

Code Example 11: `ReactorChannel.submit(Msg...)` Example

6.7.2 Writing Data Using ReactorChannel.submit(TransportBuffer...)

The `ReactorChannel.submit(TransportBuffer...)` method offers efficient writing of data by using buffers retrieved directly from the Enterprise Transport API transport buffer pool. It also provides additional features not normally available from `ReactorChannel.submit`, such as buffer packing. When ready to send data, the application acquires a buffer from the Enterprise Transport API pool. This allows the content to be encoded directly into the output buffer, reducing the number of times the content needs to be copied. Once content is encoded and the buffer is properly populated, the application can submit the data to the reactor. The Enterprise Transport API will ensure that successfully submitted buffers reach the network. Applications can also pack multiple messages into a single buffer by following a similar process as described above, however instead of getting a new buffer for each message the application uses the reactor's pack function instead. The following flow chart depicts the typical write process.




Figure 7. Flow Chart for writing data using `ReactorChannel.Submit(ITransportBuffer...)`

6.7.2.1 Obtaining a Buffer: Overview

Before you can submit information, you must obtain a buffer from the internal Enterprise Transport API buffer pool, as described in the Enterprise Transport API Java Edition *Developers Guide*. After acquiring the buffer via `ReactorChannel.getBuffer`, you can populate the `TransportBuffer.data`. If the buffer is not used or the `ReactorChannel.submit(TransportBuffer...)` method call fails, the buffer must be released back into the pool to ensure proper reuse and cleanup. If the buffer is successfully passed to `ReactorChannel.submit(TransportBuffer...)`, the reactor will return the buffer to the pool.

The number of buffers made available to an `ReactorChannel` is configurable through the `ReactorConnectOptions` or `ReactorAcceptOptions`. For more information about available `Reactor.connect` and `Reactor.accept` options, refer to Section 6.4.1.2 and Section 6.4.1.7.

6.7.2.2 Obtaining a Buffer: ReactorChannel Buffer Management Methods

METHOD NAME	DESCRIPTION
ReactorChannel.getBuffer	<p>Obtains a buffer of the requested size from the buffer pool.</p> <p>If the requested size is larger than the <code>maxFragmentSize</code>, the transport will create and return the buffer to the user. When written, this buffer will be fragmented by the <code>ReactorChannel.submit</code> method (for further details, refer to Section 6.7.2.4).</p> <p>Because of some additional book keeping required when packing, the application must specify whether a buffer should be ‘packable’ when calling <code>ReactorChannel.getBuffer</code>. For more information on packing, refer to Section 6.7.2.11.</p> <p>For performance purposes, an application is not permitted to request a buffer larger than <code>maxFragmentSize</code> and have the buffer be ‘packable.’</p> <p>If the buffer is not used or the <code>ReactorChannel.submit</code> call fails, the buffer must be returned to the pool using <code>ReactorChannel.releaseBuffer</code>. If the <code>ReactorChannel.submit</code> call is successful, the buffer will be returned to the correct pool by the transport.</p> <p>This method calls the <code>Channel.getBuffer</code> method which has its use and return values described in the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>
ReactorChannel.releaseBuffer	<p>Releases a buffer back to the correct pool. This should only be called with buffers that originate from <code>ReactorChannel.getBuffer</code> and are not successfully passed to <code>ReactorChannel.submit</code>.</p> <p>This method calls the Enterprise Transport API <code>ReactorChannel.releaseBuffer</code> method which has its use and return values described in the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>
bufferUsage	<p>Returns the number of buffers currently in use by the <code>ReactorChannel</code>, this includes buffers that the application holds and buffers internally queued and waiting to be flushed to the connection by the <code>Reactor</code>.</p> <p>This method calls the <code>Channel.bufferUsage</code> method which has its use and return values described in the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>

Table 52: ReactorChannel Buffer Management Methods

6.7.2.3 Obtaining a Buffer: `ReactorChannel.getBuffer` Return Values

The following table defines return and error code values that can occur while using `ReactorChannel.getBuffer`.

RETURN CODE	DESCRIPTION
Valid buffer returned Success Case	A <code>TransportBuffer</code> is returned to the user. The <code>TransportBuffer.length</code> indicates the number of bytes available to populate and the <code>TransportBuffer.data</code> provides a <code>ByteBuffer</code> for population.
NULL buffer returned Error Code: NO_BUFFERS	NULL is returned to the user. This value indicates that there are no buffers available to the user. See <code>ReactorErrorInfo</code> content for more details. This typically occurs because all available buffers are queued and pending flushing to the connection. The <code>ReactorChannel.ioctl</code> function can be used to increase the number of <code>guaranteedOutputBuffers</code> (for details, refer to Section 6.11).
NULL buffer returned Error Code: FAILURE	NULL is returned to the user. This value indicates that some type of general failure has occurred. The <code>ReactorChannel</code> should be closed.
NULL buffer returned Error Code: INIT_NOT_INITIALIZED	Indicates that the underlying Transport API Transport has not been initialized. See the <code>ReactorErrorInfo</code> content for more details.

Table 53: `ReactorChannel.getBuffer` Return Values

6.7.2.4 Writing Data: Overview

After a `TransportBuffer` is obtained from `ReactorChannel.getBuffer` and populated with the user's data, the buffer can be passed to the `ReactorChannel.submit` method. This method manages queuing and flushing of user content. It will also perform any fragmentation or compression. If an unrecoverable error occurs, any `TransportBuffer` that has not been successfully passed to `ReactorChannel.submit` should be released to the pool using `ReactorChannel.releaseBuffer`. Section 6.7.2.5 describes the `ReactorChannel.submit` method and its associated parameters.

6.7.2.5 Writing Data: `ReactorChannel.submit(TransportBuffer...)` Method

METHOD NAME	DESCRIPTION
submit	Writes data. This method expects the buffer to be properly populated. This method calls the Enterprise Transport API <code>Channel.write</code> method and also triggers the <code>Channel.flush</code> method (described in the Enterprise Transport API Java Edition <i>Developers Guide</i>). This method allows for several modifications and additional parameters to be specified via the <code>ReactorChannel.submit</code> object, defined in Section 6.7.1.2. For a list of return codes, refer to Section 6.7.2.8.

Table 54: `ReactorChannel.submit` Method

6.7.2.6 Writing Data: Reactor Submit Options

For a list of submit options and their descriptions for use with `ReactorChannel.submit(TransportBuffer...)`, refer to Section 6.7.1.2.

6.7.2.7 Writing Data: `ReactorRequestMsgOptions`

For a list of request message options and their descriptions for use with `ReactorChannel.submit(TransportBuffer...)`, refer to Section 6.7.1.4.

6.7.2.8 Writing Data: `ReactorChannel.submit(TransportBuffer...)` Return Codes

The following table defines the return codes that can occur when using `ReactorChannel.submit`.

RETURN CODE	DESCRIPTION
ReactorReturnCodes.SUCCESS	Indicates that the <code>ReactorChannel.submit</code> method has succeeded. The <code>TransportBuffer</code> will be released by the Enterprise Transport API Reactor.
ReactorReturnCodes.WRITE_CALL AGAIN	Indicates that a large buffer could not be fully written with this <code>ReactorChannel.submit</code> call. This is typically due to all pool buffers being unavailable. The <code>ReactorChannel.submit</code> will flush for the user to free up buffers. The application can optionally use <code>ReactorChannel.ioctl</code> to increase the number of available pool buffers. After pool buffers become available again, the same buffer should be used to call <code>ReactorChannel.submit</code> an additional time (using the same priority level for proper ordering of each fragment). This will continue the fragmentation process from where it left off. If the application does not subsequently pass the buffer to <code>ReactorChannel.submit</code> , the application should release it by calling <code>ReactorChannel.releaseBuffer</code> .
ReactorReturnCodes.FAILURE	Indicates that a general write failure has occurred. The <code>ReactorChannel</code> should be closed. The application should release the <code>TransportBuffer</code> by calling <code>ReactorChannel.releaseBuffer</code> .

Table 55: `ReactorChannel.submit` Return Codes

6.7.2.9 Writing Data: `ReactorSubmitOptions` Utility Function

For details on the utility method for use with `ReactorChannel.submit(TransportBuffer...)`, refer to Section 6.7.1.5.

6.7.2.10 Example: `ReactorChannel.getBuffer` and `ReactorChannel.submit(TransportBuffer...)` Example

The following example shows typical use of `ReactorChannel.getBuffer` and `ReactorChannel.submit(TransportBuffer...)`.

```

TransportBuffer msgBuffer = null;
EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
ReactorSubmitOptions submitOpts = ReactorFactory.createReactorSubmitOptions();

msgBuffer = reactorChannel.getBuffer(1024, false, errorInfo);

encodeIter.clear();
encodeIter.setBufferAndRWFVersion(msgBuffer, reactorChannel.majorVersion(),
    reactorChannel.minorVersion());
encodeMsgIntoBuffer(encodeIter, msgBuffer);

submitOpts.clear();
ret = reactorChannel.submit(msgBuffer, submitOpts, errorInfo);
// check return code
switch (ret)
{
    case ReactorReturnCodes.SUCCESS:
        // successful write, nothing left to do
        return ReactorReturnCodes.SUCCESS;
    break;
    case ReactorReturnCodes.FAILURE:
        // an error occurred, need to release buffer
        reactorChannel.releaseBuffer(msgBuffer, errorInfo);
    break;
    case ReactorReturnCodes.WRITE_CALL AGAIN:
        // large message couldn't be fully written with one call, pass it to submit again
        ret = reactorChannel.submit(msgBuffer, submitOpts, errorInfo);
    break;
}

```

Code Example 12: Writing Data Using `ReactorChannel.submit`, `ReactorChannel.getBuffer`, and `ReactorChannel.releaseBuffer`

6.7.2.11 Packing Additional Data into a Buffer

If an application is writing many small buffers, it may be advantageous to combine the small buffers into one larger buffer. This can increase efficiency of the transport layer by reducing the overhead associated with each write operation, although it may add to the latency associated with each smaller buffer.

It is up to the writing application to determine when to stop packing, and the mechanism used can vary greatly. A simple algorithm can pack a fixed number of messages each time. A slightly more complex technique could use the length returned from

ReactorChannel.packBuffer to determine the amount of space remaining and pack until the buffer is nearly full. Both of these mechanisms can introduce a variable amount of latency as they both depend on the rate of arrival of data (e.g., the packed buffer will not be written until enough data arrives to fill it). One way of balancing this is to employ a timer, used to limit the amount of time a packed buffer is held. If the buffer is full prior to the timer expiring, the data is written. However, when the timer expires the buffer will be written regardless of the amount of data it contains. This can help limit latency by specifying a limit to the time data is held (via use of the timer).

METHOD NAME	DESCRIPTION
ReactorChannel.packBuffer	<p>Packs the contents of a passed-in TransportBuffer and returns the amount of available bytes remaining in the buffer for packing. An application can use the length returned to determine the amount of space available to continue packing buffers into.</p> <p>For a buffer to allow packing, it must be requested from ReactorChannel.getBuffer as 'packable' and cannot exceed the maxFragmentSize.</p> <p>ReactorChannel.packBuffer return values are defined in Section 6.7.2.12.</p> <p>This method calls the Channel.packBuffer method as described in the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>

Table 56: ReactorChannel.packBuffer Method

6.7.2.12 ReactorChannel.packBuffer Return Values

The following table defines return and error code values that can occur when using **ReactorChannel.packBuffer**.

RETURN CODE	DESCRIPTION
Positive value or ReactorReturnCodes.SUCCESS Success Case	The amount of available bytes remaining in the buffer for packing.
Negative value Failure Case	This value indicates that some type of failure has occurred. If the FAILURE return code is returned, the ReactorChannel should be closed.

Table 57: ReactorChannel.packBuffer Return Values

6.7.2.13 Example: `ReactorChannel.getBuffer`, `ReactorChannel.packBuffer`, and `ReactorChannel.submit(TransportBuffer...)`

The following example shows typical use of `ReactorChannel.getBuffer`, `ReactorChannel.packBuffer`, and `ReactorChannel.submit(TransportBuffer...)`.

```

int remainingLength = 0;
TransportBuffer msgBuffer = null;
EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
ReactorSubmitOptions submitOpts = ReactorFactory.createReactorSubmitOptions();

/* get a packable buffer */
msgBuffer = reactorChannel.getBuffer(1024, true, errorInfo);

encodeIter.clear();
encodeIter.setBufferAndRWFVersion(msgBuffer, reactorChannel.majorVersion(),
    reactorChannel.minorVersion());
encodeMsgIntoBuffer(encodeIter, msgBuffer);

/* pack first encoded message into buffer */
remainingLength = reactorChannel.packBuffer(msgBuffer, errorInfo);

encodeIter.clear();
encodeIter.setBufferAndRWFVersion(msgBuffer, reactorChannel.majorVersion(),
    reactorChannel.minorVersion());
encodeMsgIntoBuffer(encodeIter, msgBuffer);

/* pack second encoded message into buffer */
remainingLength = reactorChannel.packBuffer(msgBuffer, errorInfo);

encodeIter.clear();
encodeIter.setBufferAndRWFVersion(msgBuffer, reactorChannel.majorVersion(),
    reactorChannel.minorVersion());

/* now write packed buffer by passing third buffer to submit */
encodeMsgIntoBuffer(encodeIter, msgBuffer);

submitOpts.clear();
ret = reactorChannel.submit(msgBuffer, submitOpts, errorInfo);

```

Code Example 13: Message Packing using `ReactorChannel.packBuffer`

6.8 Creating and Using Tunnel Streams

The Reactor allows users to create and use special tunnel streams. A tunnel stream is a private stream with additional behaviors, such as end-to-end line of sight for authentication and guaranteed delivery. Tunnel streams are founded on the private streams concept, and the Enterprise Transport API establishes them between consumer and provider endpoints (passing through any intermediate components, such as Refinitiv Real-Time Distribution System or a Refinitiv Real-Time Edge Device).

When creating a tunnel, the consumer indicates any additional behaviors to enforce, which is exchanged with the provider application endpoint. The provider end-point acknowledges creation of the stream as well as the behaviors that it will enforce on the stream. After the stream is established, the consumer can exchange any content it wants, though the tunnel stream will enforce behaviors on the transmitted content as negotiated with the provider.

A tunnel stream allows for multiple substreams to exist, where substreams follow from the same general stream concept, except that they flow and coexist within the confines of a tunnel stream.

In the following diagram, the orange cylinder represents a tunnel stream that connects the consumer application to the provider application. Notice that the tunnel stream passes directly through intermediate components: the tunnel stream has end-to-end line of sight so that the provider and consumer effectively talk to one another directly, though they traverse multiple devices in the system. Each black line flowing through the cylinder represents a different substream, where each substream transmits its own independent stream of information. Each substream could communicate different market content; for example one could be a Time Series request while another could be a request for Market Price content.




Figure 8. Tunnel Stream Illustration

6.8.1 Authenticating a Tunnel Stream

Providers might require the consumer to authenticate itself when establishing the tunnel stream. The type of authentication, if any, is given by the `ClassOfService.authentication.type`. For more information on class or service, refer to Section 6.8.3.

The `ClassOfService.authentication.type` may be set to `OMM_LOGIN`. When an OMM consumer expects this type of authentication, it should set a `LoginRequest` message on the `TunnelStreamOpenOptions.authLoginRequest` member. If the OMM consumer application does not provide it, the API will use the login request provided on the `ConsumerRole.rdmLoginRequest` when the consumer connected (refer to Section 6.3.2). The consumer must provide one of these for authentication of this type.

The login request will be sent to the provider. When the provider sends a Login response to complete the authentication, the `TunnelStreamStatusEvent` event given to the consumer will include an `TunnelStreamAuthInfo` object with more details. OMM provider applications will see the login request as a normal message within the `TunnelStream` and should respond with a login response message via `TunnelStream.submit`.

Other types of authentication might be specified, but must be performed by both the provider and consumer applications by submitting normal `TunnelStream` messages via `TunnelStream.submit`.

The `TunnelStreamAuthInfo` object contains the following member:

MEMBER	DESCRIPTION
loginMsg	The Login message sent by the tunnel stream's provider application, which resulted in this event.

Table 58: TunnelStreamAuthInfo Members

6.8.2 Opening a Tunnel Stream

The user can create one or more tunnel streams and associate them with any `ReactorChannel`, which opens the private stream connection and negotiates any specified behaviors. Prior to opening a tunnel stream, you must implement the `StatusEventCallback`, which is described in Section 6.8.4.

6.8.2.1 ReactorChannel.openTunnelStream Method

METHOD NAME	DESCRIPTION
openTunnelStream	Begins the establishment of a tunnel stream. The <code>TunnelStream</code> is returned via the <code>TunnelStreamStatusEventCallback</code> as specified on the <code>TunnelStreamOpenOptions</code> . For more details, refer to Section 6.8.2.2.

Table 59: Reactorchannel.openTunnelStream Method

6.8.2.2 TunnelStreamOpenOptions

The **TunnelStreamOpenOptions** contain event handler associations and options for use in creating a tunnel stream.

CLASS MEMBER	DESCRIPTION
domainType	Indicates the domain for which the tunnel stream is established. Set this to the domain specified on the service on which the Enterprise Transport API opens the tunnel stream.
streamId	Indicates the stream ID to use for the tunnel stream. Though substreams will flow within this stream ID, each will have their own independent stream ID. For example, a tunnel stream can have an ID of 10. If a substream is opened to retrieve TRI data, the substream can have a stream ID of 5, though it is encapsulated in the tunnel stream whose stream ID is 10.
serviceId	Indicates the service ID of the service on which you open the tunnel stream.
userSpecObject	Indicates a user-specified object passed in via these options and then associated with the TunnelStream .
statusEventCallback	Specifies an instance of the callback for TunnelStreamStatusEvents , which provides the TunnelStream on initial connection, and after the tunnel stream is established, communicates the tunnel stream's state information. For further details, refer to Section 6.8.4.
queueMsgCallback	Specifies the instance of the callback used to handle Queue Messages received on this TunnelStream . <ul style="list-style-type: none"> For details on the TunnelStreamQueueMsgCallback, refer to Section 6.8.4. For details on various Queue Messages, refer to Section 8.6.
defaultMsgCallback	Specifies the instance of the callback that handles all other content received on this TunnelStream . For further details, refer to Section 6.8.4.
name	Specifies the tunnel stream name. name cannot be longer than 255 characters.
responseTimeout	Sets the duration (in seconds) to wait for a provider to respond to a tunnel stream open request. If the provider does not respond in time, a TunnelStreamStatusEvent is sent to the application to indicate that the tunnel stream was not opened.
guaranteedOutputBuffers	Sets the number of guaranteed output buffers available for the tunnel stream.
authLoginRequest	Specifies the login request to send if ClassOfService.authentication.type is set to OMM_LOGIN . If absent, the API uses the login request provided on the ConsumerRole.rdmLoginRequest .
classOfService	The class of service of the tunnel stream to be opened. For further details on ClassOfService , refer to Section 6.8.3.

Table 60: TunnelStreamOpenOptions

6.8.3 Negotiating Stream Behaviors: Class of Service

ClassOfService is used to negotiate **TunnelStream** behaviors. Negotiated behaviors are divided into five categories: common, authentication, flow control, data integrity, and guarantee.

- When a consumer application calls **ReactorChannel.openTunnelStream**, it sets the **TunnelStreamOpenOptions.classOfService** members to manage and control tunnel stream behaviors. The consumer passes these settings to the connected provider.
- When a provider application receives an **TunnelStreamRequestEvent**, the provider calls **TunnelStreamRequestEvent.classOfService** to retrieve the behaviors requested by the consumer.

After tunnel stream negotiation is complete, the provider and consumer each receive a **TunnelStreamStatusEvent** where each can view the negotiated behaviors on the **TunnelStream** object.

NOTE: Do not modify the **ClassOfService** member of the **TunnelStream**.

The enumerations given for members described in this section can be found in **com.refinitiv.eta.rdm.ClassesOfService**.

6.8.3.1 ClassOfService Common Member

Common elements describe options related to the exchange of messages, such as the maximum message size and desired exchange protocol.

MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
maxFragmentSize	6144	1 – 2,147,483,647	The maximum size of message fragments exchanged on the tunnel stream. This value is set only by providers when accepting a tunnel stream.
maxMsgSize	614400	1 – 2,147,483,647	The maximum size of messages exchanged on the tunnel stream. This value is set only by providers when accepting a tunnel stream.
protocolMajorVersion	Codec.majorVersion()	0 – 255	The major version of the protocol specified by protocolType .
protocolMinorVersion	Codec.minorVersion()	0 – 255	The minor version of the protocol specified by protocolType .
protocolType	Codec.protocolType()	0 – 255	Identifies the protocol of the messages exchanged on the tunnel stream.

Table 61: ClassOfService.common Members

6.8.3.2 ClassOfService Authentication Member

The authentication member contains options to authenticate a consumer to the corresponding provider.

MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
type	ClassesOfService. AuthenticationTypes. <i>NOT_REQUIRED</i>	ClassesOfService. AuthenticationTypes. <i>NOT_REQUIRED</i> == 0, ClassesOfService. AuthenticationTypes. <i>OMM_LOGIN</i> == 1	Indicates the type of authentication, if any, to perform on the tunnel stream. For further details on authentication, refer to Section 6.8.1.

Table 62: `ClassOfService.authentication` Members

6.8.3.3 ClassOfService Flow Control Members

The flow control member contains options related to flow control, such as the type and the allowed window of outstanding data.

MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
type	ClassesOfService. FlowControlTypes. <i>NONE</i>	ClassesOfService. FlowControlTypes. <i>NONE</i> == 0, ClassesOfService. FlowControlTypes. <i>BIDIRECTIONAL</i> == 1	Indicates the type of flow control (if any) to apply to the tunnel stream.
recvWindowSize	-1	0 – 2,147,483,647	Sets the amount of data (in bytes) that the remote peer can send to the application over a reliable tunnel stream. If type is set to NONE , this parameter has no effect. -1 indicates that the application wants to use the default value for the negotiated flow control type. In this case, if type is set to BIDIRECTIONAL , the default is 12288 .
sendWindowSize	None	0 – 2,147,483,647	Indicates the amount of data (in bytes) the application can send to the remote peer on a reliable tunnel stream. This value is provided on the TunnelStream object and does not need to be set when opening or accepting a tunnel stream. This value is retrieved from the remote end and is informational, as flow control is performed by the API. When room is available in the window, the API transmits more content as submitted by the application. If type is set to NONE , this parameter has no effect.

Table 63: `ClassOfService.flowControl` Members

6.8.3.4 ClassOfService Data Integrity Member

The data integrity member contains options related to the reliability of content exchanged over the tunnel stream.

MEMBER	DEFAULT	RANGE	DESCRIPTION
type	ClassesOfService. DataIntegrityTypes. BEST_EFFORT	ClassesOfService. DataIntegrityTypes. BEST_EFFORT == 0, ClassesOfService. DataIntegrityTypes. RELIABLE == 1	Sets the level of reliability for message transmission on the tunnel stream. If set to RELIABLE , data is retransmitted as needed over the tunnel stream to ensure that all messages are delivered in the correct order. NOTE: At this time, RELIABLE is the only supported option.

Table 64: `ClassOfService.dataIntegrity` Members

6.8.3.5 ClassOfService Guarantee Members

The guarantee member contains options related to the guarantee of content submitted over the tunnel stream.

Consumer applications performing Queue Messaging to a Queue Provider should set the `ClassOfService.guarantee.type` to `ClassesOfService.GuaranteeTypes.PERSISTENT_QUEUE`.

MEMBER	DEFAULT	RANGE	DESCRIPTION
type	ClassesOfService. GuaranteeTypes. NONE	ClassesOfService. GuaranteeTypes. NONE == 0, ClassesOfService. GuaranteeTypes. PERSISTENT_QUEUE == 1	Indicates the level of guarantee that will be performed on this stream. PERSISTENT_QUEUE is not supported for provider applications. NOTE: If <code>type</code> is set to PERSISTENT_QUEUE for a consumer application, the data integrity <code>type</code> must also be set to RELIABLE and the flow control <code>type</code> to BIDIRECTIONAL .
persistLocally	true	false, true	Indicates whether messages are persisted locally on the tunnel stream. When <code>type</code> is NONE , this member has no effect.
persistenceFilePath	NULL	n/a	File path where files containing persistent messages may be stored. If set to NULL, the current working directory is used. When <code>type</code> is NONE , or when <code>persistLocally</code> is set to false , this member has no effect.

Table 65: `ClassOfService.guarantee` Members

6.8.4 Tunnel Stream Callback Methods and Event Types

6.8.4.1 Tunnel Stream Callback Methods

The **TunnelStream** delivers events via the following user-implemented callback methods. These callback methods return event objects as defined in Section 6.8.4.2.

CALLBACK METHOD	DESCRIPTION
statusEventCallback	Communicates status information about the tunnel stream. Additionally, this callback delivers the TunnelStream object after the enhanced private stream is established. This callback provides a TunnelStreamStatusEvent to the application. Details about this event are available in Section 6.8.4.2.
defaultMsgCallback	Similar to the ReactorChannel.defaultMsgCallback , content received by the tunnel stream are returned via this callback if it is not handled by a more specific content handler, such as the queueMsgCallback . This callback provides a TunnelStreamMsgEvent to the application. Details about this event are available in Section 6.8.4.2.
queueMsgCallback	Any queue messages are delivered via this callback and presented to the user in their native queue message formats. If unspecified, queue messages are delivered via the defaultMsgCallback ; however they are not presented in a queue message format. This callback provides a TunnelStreamQueueMsgEvent to the application. Details about this event are available in Section 6.8.4.2.

Table 66: Tunnel Stream Callback Methods

6.8.4.2 Tunnel Stream Callback Event Types

Various tunnel stream callbacks return their information via specific event objects. The following table defines these events.

EVENT	EVENT DESCRIPTION	CLASS MEMBER	CLASS MEMBER DESCRIPTION
TunnelStreamStatusEvent	This event presents the tunnel stream and its status.	tunnelStream	Returns the TunnelStream associated with this event. When the TunnelStream is initially opened, the initial instance of the TunnelStream is made available.
		state	Indicates status information associated with the TunnelStream . For example: <ul style="list-style-type: none"> A state of OPEN and OK indicates that the tunnel stream is established and content should be flowing as expected. A state of CLOSED_RECOVER or SUSPECT indicates that the connection or tunnel stream might be lost. However, if performing guaranteed messaging, content might be persisted by the reactor and communicated upon recovery of the tunnel stream.
		authInfo	(Consumers only) Provides information about a received authentication response.
TunnelStreamMsgEvent	This event presents content received on the TunnelStream . If a more specific handler (i.e., queueMsgCallback) is also configured, messages of that type will go to their specific handler.	tunnelStream	Returns the TunnelStream associated with this event.
		msg	Contains the content being presented to the user. <ul style="list-style-type: none"> If content adheres to the OMM, it is partially decoded for user convenience. If content is opaque, a buffer housing the contents is presented to the user via this object.
		transportBuffer	The transport buffer associated with this event.
		containerType	The container type associated with this event's transport buffer.
TunnelStreamQueueMsgEvent	This event presents any queue message content received on the TunnelStream .	tunnelStream	Returns the TunnelStream associated with this event.
		queueMsg	Contains the content being presented to the user, presented as a queue message object.

Table 67: Tunnel Stream Callback Event Types

6.8.5 Code Sample: Opening and Managing a Tunnel Stream

The following code sample is a basic example of opening a tunnel stream. The example assumes that a **Reactor** and **ReactorChannel** are already open and properly established.

```
// Basic sample for event handlers
class Sample implements StatusEventCallback, TunnelStreamQueueMsgCallback,
    TunnelStreamDefaultMsgCallback
{
    ReactorErrorInfo _errorInfo;

    // StatusEventCallback
    public int statusEventCallback(TunnelStreamStatusEvent event)
    {
        System.out.println("Status of Tunnel Stream (" + event.tunnelStream().streamId() + ") is " +
            event.state());
        Return ReactorCallbackReturnCodes.SUCCESS;
    }

    // TunnelStreamDefaultMsgCallback
    public int TunnelStreamDefaultMsgCallback(TunnelStreamMsgEvent event)
    {
        System.out.println("Received content on Tunnel Stream (" + event.tunnelStream().streamId() +
            ")");
        Return ReactorCallbackReturnCodes.SUCCESS;
    }

    // TunnelStreamQueueMsgCallback
    public int tunnelStreamQueueMsgCallback(TunnelStreamQueueMsgEvent event)
    {
        System.out.println("Received Queue Message on Tunnel Stream (" +
            event.tunnelStream().streamId() + ")");
        Return ReactorCallbackReturnCodes.SUCCESS;
    }
}

int openTunnelStream()
{
    TunnelStreamOpenOptions _openOptions = RectorFactory.createTunnelStreamOpenOptions();

    // populate the options and enable guaranteed delivery for communication with a Queue Provider
    _openOptions.streamId(TUNNEL_STREAM_ID);
    _openOptions.domainType(DomainTypes.QUEUE_MESSAGING);
    _openOptions.serviceId(QUEUE_MESSAGING_SERVICE_ID);
    // specify the event handlers
    _openOptions.statusEventCallback(this);
    _openOptions.TunnelStreamDefaultMsgCallback(this);
    _openOptions.queueMsgCallback(this);

    if ((reactorChannel.openTunnelStream(_openOptions, _errorInfo)) != ReactorReturnCodes.SUCCESS)
```

```

{
    System.out.println("openTunnelStream failed!");
    return ReactorReturnCodes.FAILURE;
}

System.out.println("openTunnelStream succeeded!");
return ReactorReturnCodes.SUCCESS;
}

```

Code Example 14: Opening a Tunnel Stream

6.8.6 Accepting Tunnel Streams

OMM provider applications can accept tunnel streams provided on an `ReactorChannel` (enabled by specifying a `tunnelStreamListenerCallback` on the `ProviderRole`).

When a consumer opens a tunnel stream, the `tunnelStreamListenerCallback` receives an `TunnelStreamRequestEvent`. At this point, the provider should call `TunnelStreamRequestEvent.classOfService` to retrieve the `ClassOfService` requested by the tunnel stream and ensure that the parameters indicated by the members of that class of service match what the provider allows. The provider can also check the `TunnelStreamRequestEvent.classOfServiceFilter` to determine which behaviors the consumer supports. For more information on this filter, refer to Section 6.8.6.1.

- To accept a tunnel stream, the provider must call `ReactorChannel.acceptTunnelStream` with the given `TunnelStreamRequestEvent`. Further events regarding the accepted stream are provided in the specified `TunnelStreamAcceptOptions.statusEventCallback`.
- To reject a tunnel stream, the provider calls `ReactorChannel.rejectTunnelStream` with the given `TunnelStreamRequestEvent`. No further events are received for that tunnel stream.

Queue messaging (a `ClassOfService.guarantee.type` setting of `PERSISTENT_QUEUE`) is not supported for provider applications.

The API automatically rejects tunnel streams that contain invalid information. When this happens, the provider application receives warnings via a `ReactorChannelEvent`. The type will be set to `ReactorChannelEventTypes WARNING` and the `ReactorErrorInfo` in the event will contain text describing the reason for the rejection.



Warning! Ensure that the provider application calls `ReactorChannel.acceptTunnelStream` or `ReactorChannel.rejectTunnelStream` before returning from the `tunnelStreamListenerCallback`. If not, the provider application will receive a warning via an `ReactorChannelEvent` similar to the above, and the stream will be automatically rejected.

6.8.6.1 Reactor Tunnel Stream Listener Callback

Providers that want to handle tunnel streams from connected consumers can specify a **TunnelStreamListenerCallback**. This callback informs the provider application of any consumer tunnel stream requests.

The provider can specify this callback function on the **ProviderRole**, which has the following signature:

```
listenerCallback(TunnelStreamRequestEvent event);
```

For more information on the **ProviderRole**, refer to Section 6.3.3.

A **TunnelStreamRequestEvent** is returned to the application via the **TunnelStreamListenerCallback**.

MEMBER	DESCRIPTION
reactorChannel	Specifies the ReactorChannel on which the event was received.
streamId	Specifies the stream ID of the requested tunnel stream.
domainType	Specifies the domain type of the requested tunnel stream.
serviceId	Specifies the service ID of the requested tunnel stream.
name	Specifies the name of the requested tunnel stream.
classOfServiceFilter	Sets a filter that indicates which ClassOfService members are present. The provider can use this filter to determine whether behaviors are supported by the consumer and if needed, reject the tunnel stream before calling TunnelStreamRequestEvent.classOfService to get the full ClassOfService . For enumerations of the flags present in this filter, refer to com.refinitiv.eta.rdm.ClassesOfService.FilterFlags .
classOfService	Specifies the ClassOfService for the requested tunnel stream.

Table 68: **TunnelStreamRequestEvent** Members

6.8.6.2 ReactorChannel.acceptTunnelStream Method

METHOD NAME	DESCRIPTION
ReactorChannel.acceptTunnelStream	Accepts a tunnel stream requested by a consumer. The TunnelStream is returned in the TunnelStreamStatusEventCallback specified on the TunnelStreamAcceptOptions . For more information, refer to Section 6.8.6.3.

Table 69: **Reactorchannel.acceptTunnelStream** Method

6.8.6.3 TunnelStreamAcceptOptions

OPTION	DESCRIPTION
statusEventCallback	Specifies the instance of the callback for TunnelStreamStatusEvents , which provides the TunnelStream on initial connection and then communicates state information about the tunnel afterwards. For details on the TunnelStreamStatusEventCallback , refer to Section 6.8.4.1.
defaultMsgCallback	Specifies the instance of the callback used to handle all other content received on this TunnelStream . For details on TunnelStreamdefaultMsgCallback , refer to Section 6.8.4.1.
userSpecObject	Specifies a user-defined object passed in via these options and then associated with the TunnelStream .
classOfService	Specifies an ClassOfService with members indicating behaviors that the application wants to apply to the TunnelStream . For more information on class of service, refer to Section 6.8.3.
guaranteedOutputBuffers	Sets the number of pooled buffers available to the application when writing content to TunnelStream .

Table 70: **TunnelStreamAcceptOptions** Options

6.8.6.4 ReactorChannel.rejectTunnelStream

METHOD NAME	DESCRIPTION
ReactorChannel.rejectTunnelStream	Rejects a tunnel stream requested by a consumer. No further events will be received for this tunnel stream. For more information, refer to Section 6.8.6.5.

Table 71: **ReactorChannel.rejectTunnelStream** Method

6.8.6.5 TunnelStreamRejectOptions

OPTION	DESCRIPTION
state	A State to send to the consumer. The application can use the state.streamState , state.dataState , and state.text to indicate the nature of the rejection.
expectedClassOfService	An optional ClassOfService to send to the consumer. If rejecting the stream due to a problem with the ClassOfService parameters from the TunnelStreamRequestEvent , the provider application should populate this with the associated parameters.

Table 72: **TunnelStreamRejectOptions** Options

6.8.6.6 Accepting a Tunnel Stream Code Sample

The following code illustrates how to accept a tunnel stream requested by a consumer. The example presumes that a **Reactor** and **ReactorChannel** are already open and properly established.

```

public int listenerCallback(TunnelStreamRequestEvent event)
{
    int ret;
    TunnelStreamAcceptOptions acceptOpts = ReactorFactory.createTunnelStreamAcceptOptions();

    if (isFilterValid(event.classOfServiceFilter()) &&
        isClassOfServiceValid(event.classOfService()))
    {
        acceptOpts.clear();

        // set class of service to what this provider supports
        acceptOpts.classOfService().dataIntegrity().type(ClassesOfService.DataIntegrityTypes.RELIABLE
            );
        acceptOpts.classOfService().flowControl().type((ClassesOfService.FlowControlTypes.
            BIDIRECTIONAL));

        // Set Authentication to match consumer. This provider will perform OMM Login authentication if
        // requested.
        acceptOpts.classOfService().authentication().type(event.classOfService().authentication().
            type());

        acceptOpts.statusEventCallback(this);
        acceptOpts.defaultMsgCallback(this);

        if ((ret = event.reactorChannel().acceptTunnelStream(event, acceptOpts, event.errorInfo())))
            < ReactorReturnCodes.SUCCESS)
        {
            System.out.println("acceptTunnelStream() failed with return code: " + ret + " <" +
                event.errorInfo().error().text() + ">");
        }
    }

    return ReactorCallbackReturnCodes.SUCCESS
}

```

Code Example 15: Accepting a Tunnel Stream Code Example

6.8.6.7 Rejecting a Tunnel Stream Code Sample

The following code illustrates how to reject a tunnel stream requested by a consumer. The example assumes that a **Reactor** and **ReactorChannel** are already open and properly established.

```
public int listenerCallback(TunnelStreamRequestEvent event)
{
    int ret;

    /* Now presuming that the application wishes to reject the tunnel stream because the requested
     * class of service is invalid. */

    if (!isFilterValid(event.classOfServiceFilter()) || !isClassOfServiceValid(event.classOfService()))
    {
        /* Set what the class of service is expected to be. */
        ClassOfService expectedCos = ReactorFactory.createClassOfService();
        expectedCos.clear();
        expectedCos.authentication().type(ClassesOfService.AuthenticationTypes.OMM_LOGIN);
        expectedCos.flowControl().type(ClassesOfService.FlowControlTypes.BIDIRECTIONAL);
        expectedCos.dataIntegrity().type(ClassesOfService.DataIntegrityTypes.RELIABLE);
        /* ... (set additional members, based on what is desired by the provider) */

        TunnelStreamRejectOptions rejectOpts = ReactorFactory.createTunnelStreamRejectOptions();
        rejectOpts.clear();
        rejectOpts.state().streamState(StreamStates.CLOSED);
        rejectOpts.state().dataState(DataStates.SUSPECT);
        rejectOpts.state().code(StateCodes.NONE);
        rejectOpts.state().text().data("Unsupported TunnelStream class of service");
        rejectOpts.expectedClassOfService(expectedCos);

        if ((ret = event.reactorChannel().rejectTunnelStream(event, rejectOpts, event.errorInfo())) <
            ReactorReturnCodes.SUCCESS)
        {
            System.out.println("rejectTunnelStream() failed with return code: " + ret + " <" +
                event.errorInfo().error().text() + ">");
        }
    }

    return ReactorCallbackReturnCodes.SUCCESS
}
```

Code Example 16: Rejecting a Tunnel Stream Code Example

6.8.7 Receiving Content on a TunnelStream

Invoking the `ReactorChannel.dispatch` method reads and processes inbound content, where any information received on this `TunnelStream` will be delivered to the application via the tunnel stream callback methods specified via `openTunnelStream` or `ReactorChannel.acceptTunnelStream`.

Dispatching this content works in the same manner as dispatching any other content on the reactor.

- Tunnel stream callback methods are described in Section 6.8.4.
- Tunnel stream callback methods deliver the events described in Section 6.8.4.2.

6.8.8 Sending Content on a TunnelStream

When you send content on a `TunnelStream`: get a buffer from the `TunnelStream`, encode your content into the buffer, and then use the `TunnelStream.submit` method to push the content out over the `TunnelStream`. By obtaining a buffer from the `TunnelStream`, the reactor can then properly handle any negotiated behaviors, making this functionality nearly transparent.

6.8.8.1 Tunnel Stream Buffer Methods

METHOD NAME	DESCRIPTION
getBuffer	Obtains a buffer from the <code>TunnelStream</code> . To properly enforce negotiated behaviors on content in the buffer, the Enterprise Transport API associates the buffer with the tunnel stream from which it is obtained.
info	Gets information about the Tunnel Stream by returning the <code>TunnelStreamInfo</code> structure. For details on <code>TunnelStreamInfo</code> methods, refer to Section 6.8.8.4.
releaseBuffer	<p>Releases a buffer back to the <code>TunnelStream</code> from which it came. You should release any buffer that you do not submit. Releasing the buffer ensures it is properly recycled and can be reused.</p> <p>NOTE: If you submit a buffer properly, you do not need to release it, because the submit method automatically releases it after sending the content on the <code>TunnelStream</code>.</p>

Table 73: Tunnel Stream Buffer Methods

6.8.8.2 Tunnel Stream Submit

The submit method is used to write content to the `TunnelStream`. This method also enforces any specified behaviors on submitted content (e.g., if guaranteed messaging is specified, this content follows all configured persistence options).

METHOD NAME	DESCRIPTION
submit	<p>Use the submit method to pass in opaque or RDM message content (including Queue Messages) to be processed and sent over the <code>TunnelStream</code>.</p> <p>This method has additional options that can be specified via <code>TunnelStreamSubmitOptions</code> (refer to Section 6.8.8.3).</p>

Table 74: Tunnel Stream Submit Method

6.8.8.3 TunnelStream.submit Option

When calling `TunnelStream.submit` with a buffer, you can use `TunnelStreamSubmitOptions` to provide the `containerType` option.

MEMBER	DESCRIPTION
containerType	<p>Specifies the type of data in the buffer being submitted.</p> <p>For example:</p> <ul style="list-style-type: none"> If the submitted buffer contains a <code>Msg</code>, set <code>containerType</code> <code>DataTypes.MSG</code>. If sending non-RWF data, set <code>containerType</code> to a non-RWF type, such as <code>DataTypes.OPAQUE</code>. <p>For more information on possible container types, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>

Table 75: `TunnelStreamSubmitOptions` Members

6.8.8.4 TunnelStreamInfo Methods

The following table describes values available when using the `TunnelStream.info` method (for details, refer to Section 6.8.8.1). This information is returned as part of the `TunnelStreamInfo` object.

METHOD NAME	DESCRIPTION
<code>bigBuffersUsed</code>	Returns the number of big buffers used by user application.
<code>buffersUsed</code>	Returns the total number of buffers used by the Tunnel Stream for a user application.
<code>ordinaryBuffersUsed</code>	Returns the total number of buffers with a size less than or equal to 6144 bytes used by Tunnel Stream for a user application. Java implementation maintains an internal pool, thus you can allocate buffer space in advance and use buffer space when needed for <code>TunnelStream.getBuffer</code> calls.

Table 76: `TunnelStreamInfo` Methods

6.8.8.5 Submitting Content on a Tunnel Stream Code Sample

The following code sample is a basic example of writing opaque content to a tunnel stream. You can combine this example with the QueueData message samples in subsequent chapters to send content to a Queue Provider.

```

int submitMessage()
{
    TunnelStreamSubmitOptions _submitOpts = ReactorFactory.createTunnelStreamSubmitOptions();

    // gets a buffer of 50 bytes to put content into.
    TransportBuffer _buffer = tunnelStream.getBuffer(50, _errorInfo);

    // put generic content into the buffer
    _buffer.data().put("Hello World!");
    _submitOpts.containerType(DataTypes.OPAQUE);

    if ((tunnelStream.submit(_buffer, _submitOpts, _errorInfo)) != ReactorReturnCodes.SUCCESS)
    {
        System.out.println("Content submission failed!");
    }
}

```

```

// Because submission failed, we need to return the buffer to the tunnel stream
tunnelStream.releaseBuffer(_buffer, _errorInfo);

return ReactorReturnCodes.FAILURE;
}

System.out.println("Content submission succeeded!");
// Thanks to successful submission, we do not need to release the buffer because the Reactor will.
return ReactorReturnCodes.SUCCESS;
}

```

Code Example 17: Submitting Content on a Tunnel Stream**6.8.9 Closing a Tunnel Stream**

When an application has completed its use of a **TunnelStream**, close it using the **close** method.

6.8.9.1 Tunnel Stream Close

METHOD NAME	DESCRIPTION
close	Closes a tunnel stream. After you close a tunnel stream, the Enterprise Transport API cleans up any data that was stored for guaranteed messaging or reliable delivery. The finalStatusEvent argument indicates that the application wants to receive a final TunnelStreamStatusEvent whenever the tunnel stream closes. If this is set to true , the tunnel stream will be cleaned up after the application receives the final TunnelStreamStatusEvent event.

Table 77: Tunnel Closure Method

6.8.9.2 Closing a Tunnel Stream Sample

The following code sample illustrates how to close a tunnel stream.

```

int closeTunnelStream()
{
    if ((tunnelStream.close(true, _errorInfo)) != ReactorReturnCodes.SUCCESS)
    {
        System.out.println("Closing tunnel stream failed!");
        return ReactorReturnCodes.FAILURE;
    }

    System.out.println("Tunnel Stream closed successfully.");
    return ReactorReturnCodes.SUCCESS;
}

```

Code Example 18: Closing a Tunnel Stream

6.9 Cloud Connectivity

For details on workflows and routines associated with connecting to the cloud, refer to Chapter 7.

You use the `Reactor.queryServiceDiscovery` method to query service endpoints from the EDP-RT service.

6.9.1 Querying Service Discovery

6.9.1.1 queryServiceDiscovery Method

METHOD	DESCRIPTION
queryServiceDiscovery	Queries service endpoints from the Refinitiv Real-Time Optimized service according to the <code>ReactorServiceDiscoveryOptions</code> that you specify (listed in Section 6.9.1.2). Error handling is managed by the <code>ReactorErrorInfo</code> object.

Table 78: `Reactor.queryServiceDiscovery` Method

6.9.1.2 ReactorServiceDiscoveryOptions

MEMBER	DESCRIPTION
audience	Optional and only used with Version 2 OAuth ClientCredentials with JWT logins. A <code>Buffer</code> specifies the JWT's audience claim field. By default, the Enterprise Transport API uses https://login.ciam.refinitiv.com/as/token.oauth2
clientId	Required . A <code>Buffer</code> that specifies a unique ID defined for an application making a request to the token service.
clientJWK	Required for Version 2 OAuth ClientCredentials with JWT logins. A <code>Buffer</code> that contains the JWK-formatted private key associated with the Service Account. For further information, refer to the clientSecret member in this section.
clientSecret	A <code>Buffer</code> that specifies the client secret (if one exists) used by the OAuth client to authenticate to the authorization Server.
dataFormat	Optional. An enumeration that specifies the desired data format to use when retrieving service endpoints from the service discovery. For available values, refer to Section 6.9.1.4.
password	Required . A <code>Buffer</code> that specifies a password for authorization with the token service.
proxyHostName	Optional. A <code>Buffer</code> that specifies a proxy server hostname.
proxyPort	Optional. A <code>Buffer</code> that specifies a proxy server port.
proxyUserName	Optional. A <code>Buffer</code> that specifies a username to perform authorization with a proxy server.
proxyPasswd	Optional. A <code>Buffer</code> that specifies a password to perform authorization with a proxy server.
proxyDomain	Optional. A <code>Buffer</code> that specifies the proxy domain of the user to authenticate. Required for NTLM or for Negotiate/Kerberos or for Kerberos authentication protocols.
reactorServiceEndpointEventCallback	A callback function that receives <code>ReactorServiceEndpointEventCallbacks</code> . Applications can take service endpoint information from the callback to get an endpoint and establish a connection to the service.
tokenScope	A <code>Buffer</code> that specifies an optional token scope to limit the scope of the generated token from the token service.

Table 79: `ReactorServiceDiscoveryOptions` Members

MEMBER	DESCRIPTION
transport	Optional. An enumeration that specifies the desired transport protocol to retrieve service endpoints from the service discovery. For available values, refer to Section 6.9.1.3.
userName	Required. A Buffer that specifies a user name for authorization with the token service.
userSpecObj	Optional. A user-specified pointer which is set on the ReactorServiceEndpointEvent . Also refer to Section 6.9.1.5.

Table 79: ReactorServiceDiscoveryOptions Members (Continued)**6.9.1.3 queryServiceDiscovery Transport Protocol Enumerations**

ENUMERATED NAME	DESCRIPTION
RD_TP_INIT = 0	Specifies that the transport's protocol is unknown.
RD_TP_TCP = 1	Specifies that the service discovery should use the TCP transport protocol.
RD_TP_WEBSOCKET = 2	Specifies that the service discovery should use the Websocket transport protocol.

Table 80: ReactorDiscoveryTransportProtocol Enumerations**6.9.1.4 ReactorDiscoveryDataFormatProtocol Enumerations**

ENUMERATED NAME	DESCRIPTION
RD_DP_INIT = 0	Specifies that the transport's data format is unknown.
RD_DP_RWF = 1	Specifies that the service discovery should use the RWF data format.
RD_DP_JSON2 = 2	Specifies that the service discovery should use the tr_json2 data format

Table 81: ReactorDiscoveryDataFormatProtocol Enumerations**6.9.1.5 ReactorServiceEndpointEvent**

MEMBER	DESCRIPTION
serviceEndpointInfo	Lists the service endpoints associated with this event. See also Section 6.9.1.6.
userSpecObj	Optional. A user-specified object associated with this ReactorServiceEndpointEvent .

Table 82: ReactorServiceEndpointEvent Members**6.9.1.6 ReactorServiceEndpointInfo**

ReactorServiceEndpointEvent represents service endpoint information.

MEMBER	DESCRIPTION
dataFormatList	A <code>List<String></code> that contains a list of data formats used by the transport.
endPoint	A <code>String</code> that specifies the domain name of the service access endpoint.
locationList	A <code>List<String></code> object that specifies a list of service locations.
port	A <code>String</code> that specifies the port number used to establish connection.
provider	A <code>String</code> that specifies a public cloud provider.
transport	A <code>String</code> that specifies the transport type used to access the service.

Table 83: ReactorServiceEndpointEvent Members

6.9.2 OAuth Credential Management

6.9.2.1 ReactorOAuthCredential Class

You use the `ReactorOAuthCredential` class to certify OAuth user credentials when connecting to the cloud.

`ReactorOAuthCredential` includes the following members:

MEMBER	DESCRIPTION
audience	Optional and only used with Version 2 OAuth ClientCredentials with JWT logins. A <code>Buffer</code> that specifies the JWT's audience claim field. By default, the Enterprise Transport API uses https://login.ciam.refinitiv.com/as/token.oauth2
clientId	Required . A <code>Buffer</code> that specifies an authentication parameter. <ul style="list-style-type: none"> Version 1 authentication: Client ID usage with OAuth Password Credentials. For further information, refer to Section 7.4. Version 2 authentication: a unique ID defined for the application that makes the request and is provisioned as part or a service account for the login. For further information, refer to Section 7.5.
clientJWK	Required for Version 2 OAuth ClientCredentials with JWT logins. A <code>Buffer</code> that contains the JWK-formatted private key is associated with the Service Account. For further information, refer to Section 7.5.
clientSecret	Required for Version 2 OAuth ClientCredentials logins. A <code>Buffer</code> that specifies the Service Account "secret" for authentication. For further information, refer to Section 7.5.
password	Required for Version 1 OAuth Password Credentials logins. A <code>Buffer</code> that specifies the password used in tandem with the <code>userName</code> to obtain the access token.
reactorOAuthCredentialEventCallback	A callback function that receives the <code>reactorOAuthCredentialEvent</code> to specify the <code>password</code> and/or <code>clientSecret</code> . <p>If <code>reactorOAuthCredentialEventCallback</code> is specified, the Value Added Components Reactor does not store the <code>password</code> or <code>clientSecret</code>. In which case, the application must supply the <code>password</code> whenever receiving a new refresh token. For details on this process, refer to Section 7.4.2.</p>
takeExclusiveSignOnControl	Optional and only used with Version 1 Password Credentials logins. A boolean that, if set to true, forces sign-out of any other applications using the same credentials. By default, this is set to true.

Table 84: ReactorOAuthCredential Class Members

MEMBER	DESCRIPTION
tokenScope	A Buffer that specifies the user's resource scope that defines the type of data the user accesses in the cloud. For further details on token scopes, refer to the Refinitiv Data Platform APIs tutorial called <i>Authorization - All about tokens</i> in the Developer Community Portal . By default, the Enterprise Transport API uses the scope: <code>trapi.streaming.pricing.read</code> .
userName	Required for Version 1 OAuth Password Credentials logins. A Buffer that specifies the user name used to obtain the access token from the Refinitiv Data Platform.

Table 84: ReactorOAuthCredential Class Members (Continued)

6.9.2.2 reactorOAuthCredentialEventCallback

Whenever the Enterprise Transport API needs a new refresh token, it needs to again supply the username, Client ID, and password. But the Enterprise Transport API stores only the username and Client ID, not the password. To obtain the password (and if available, the client secret), the Enterprise Transport API sends the **ReactorOAuthCredentialEvent** callback to the application.

MEMBER	DESCRIPTION
reactorOAuthCredentialEventCallback	Specifies OAuth credential renewal information associated with this event.

Table 85: ReactorOAuthCredentialEvent Members

6.9.2.3 ReactorOAuthCredentialRenewal

MEMBER	DESCRIPTION
audience	Optional and only used with Version 2 oAuth ClientCredentials with JWT logins. A Buffer that specifies the JWT's audience claim field. By default, the Enterprise Transport API uses https://login.ciam.refinitiv.com/as/token.oauth2
clientId	Required. A Buffer that specifies an authentication parameter. <ul style="list-style-type: none"> Version 1 authentication: Client ID usage with oAuth Password Credentials. For further information, refer to Section 7.4. Version 2 authentication: a unique ID defined for the application that makes the request and is provisioned as part or a service account for the login. For further information, refer to Section 7.5.
clientJWK	Required for Version 2 oAuth ClientCredentials with JWT logins. A Buffer that contains the JWK-formatted private key is associated with the Service Account. For further information, refer to Section 7.5.
clientSecret	Required for Version 2 oAuth ClientCredentials logins. A Buffer that specifies the Service Account "secret" for authentication. For further information, refer to Section 7.5.
newPassword	Conditional. A Buffer that specifies the new password when changing the password associated with the specified userName . Include newPassword only when the application wants to change its password, in which case both the current (password) and new password (newPassword) are required.
password	Required for Version 1 oAuth Password Credentials logins. A Buffer that specifies the password, which is sent with the userName to get an access token and a refresh token.

Table 86: ReactorOAuthCredentialRenewal Members

MEMBER	DESCRIPTION
tokenScope	A Buffer that specifies the scope of the generated token.
userName	Conditional. A Buffer that specifies the user name that the Enterprise Transport API sends to the Refinitiv Data Platform token service. The ReactorOAuthCredentialEventCallback also uses userName when returning sensitive information. Required for Version 1 oAuth Password Credentials logins, except when specifying sensitive information in the ReactorOAuthCredentialEventCallback .

Table 86: **ReactorOAuthCredentialRenewal** Members(Continued)

6.9.2.4 **ReactorOAuthCredentialRenewal** Options

OPTION	DESCRIPTION
reactorAuthTokenEventCallback	A callback function that receives ReactorAuthTokenEvents . The Reactor requests a token for the Consumer (i.e., disabling watchlist) and NiProvider applications to send login requests and reissues with the token. reactorAuthTokenEventCallback is needed only when changing a password without a channel in order to get a response from the request. The application does not have to send a login reissue in this case.
proxyDomain	A Buffer that specifies the domain for authenticated proxies.
proxyHostName	A Buffer that specifies the proxy's host name.
proxyPasswd	A Buffer that specifies the password for authenticated proxies.
proxyPort	A Buffer that specifies the proxy's port.
proxyUserName	A Buffer that specifies the username for authenticated proxies.
renewalMode	A ReactorOAuthCredentialRenewalMode that specifies the mode in which the Enterprise Transport API submits OAuth credential renewals. For available ENUMS and their descriptions, refer to Section 6.9.2.5.
userName	Required. A Buffer that specifies a user name for authorization with the token service.

Table 87: **ReactorOAuthCredentialRenewal** Options

6.9.2.5 **ReactorOAuthCredentialRenewalOptions.RenewalModes** Class

MODE	DESCRIPTION
PASSWORD	Use this renewal mode when normally submitting a password to obtain an access and refresh token.
PASSWORD_CHANGE	Use this renewal mode when normally submitting a password to obtain an access and refresh token.

Table 88: **ReactorOAuthCredentialRenewalMode** Enums

6.10 JSON to RWF Protocol Conversion for WebSocket Support

For the consumer to support WebSocket connection requests, you must initialize the consumer and define **WSocketOpts.protocols**, based on the types of protocol you want to support, as follows:

- To support WebSocket connections for only the RWF sub-protocol, use `ConnectOptions.wSocketOpts.protocols("rssl.rwf")`.
 - This is the only requirement. For an example of setting `wSocketOpts`, refer to Section 6.10.1.1.
 - For remaining tasks for managing the Consumer, refer to Chapter 3, Building an OMM Consumer.
- To support WebSocket connection requests for JSON2 and RWF sub-protocols (either alone, or in tandem with RWF), use `ConnectOptions.wSocketOpts.protocols("rssl.rwf, rssl.json.v2, tr_json2")`.

For details on `WSocketOpts`, refer to the *Enterprise Transport API Java Edition Developer Guide*.

To support WebSocket connections in JSON (either alone, or in tandem with RWF), after initializing the Interactive Provider, you must then perform the following:

- Connect the Consumer over an encrypted WebSocket. For an example, refer to Section 6.10.1.2.
- Define the Reactor JSON Converter event callback by using the `JsonConverterOptions.jsonConversionEventCallback()` function. For an example, refer to Section 6.10.1.3.
- Define the `ServiceName` to `ServiceId` callback (using the `JsonConverterOptions.serviceNameToIdCallback()` function). For an example, refer to Section 6.10.1.3.
- Clear and populate a JSON Converter options object using the callbacks from the preceding tasks. For an example, refer to Section 6.10.1.4.
- Initialize the Reactor JSON Converter using the `Reactor.initJsonConverter()` function passing in the JSON converter options `ReactorJsonConverterOptions`. For an example, refer to Section 6.10.2.4.
- For remaining tasks on managing the Consumer, refer to Chapter 3, Building an OMM Consumer.

6.10.1 Consumer and WebSocket Support

6.10.1.1 Example: Initializing the Consumer to Support WebSocket Connections for RWF Only

```
ConnectOptions cOpt = chnlInfo.connectOptions.connectionList().get(0).connectOptions();
cOpt.connectionType(ConnectionTypes.WEBSOCKET);
cOpt.wSocketOpts().protocols("rssl.rwf");
```

6.10.1.2 Example: Connecting the Consumer over an Encrypted WebSocket

```
ConnectOptions cOpt = chnlInfo.connectOptions().connectionList().get(0).connectOptions();
cOpt.connectionType(ConnectionTypes.ENCRYPTED);
cOpt.encryptionOptions().connectionType(ConnectionTypes.WEBSOCKET);
cOpt.wSocketOpts().protocols("rssl.rwf");
```

6.10.1.3 Example: Defining Reactor JSON Converter Event Callback and ServiceName to ServiceId Callback

```
public class JsonConversionEventCallbackImpl implements ReactorJsonConversionEventCallback {

    @Override
    public int reactorJsonConversionEventCallback(ReactorJsonConversionEvent jsonConversionEvent) {
        System.out.println("JSON Conversion error: " + jsonConversionEvent.error().text());

        return ReactorCallbackReturnCodes.SUCCESS;
    }
}

public class ServiceNameIdCallbackImpl implements ReactorServiceNameToIdCallback {

    @Override
    public int reactorServiceNameToIdCallback(ReactorServiceNameToId serviceNameToId,
                                              ReactorServiceNameToIdEvent serviceNameToIdEvent) {

        ChannelInfo chnlInfo = (ChannelInfo) serviceNameToIdEvent.reactorChannel().userSpecObj();

        /* Checks whether the service name is used by the channel. */
        if(chnlInfo.serviceInfo().checkHasInfo() && serviceNameToId.serviceName()
                .equals(chnlInfo.serviceInfo().info().serviceName().toString()))
        {
            serviceNameToId.serviceId(chnlInfo.serviceInfo().serviceId());
            return CodecReturnCodes.SUCCESS;
        }
        else
        {
            return CodecReturnCodes.FAILURE;
        }
    }
}
```

6.10.1.4 Example: Clear and Populate a JSON Converter Options Structure

```
ReactorJsonConverterOptions jsonConverterOptions = ReactorFactory.createReactorJsonConverterOptions();

jsonConverterOptions.clear();
jsonConverterOptions.dataDictionary(dictionary);
jsonConverterOptions.serviceNameToIdCallback(new ServiceNameIdCallbackImpl());
jsonConverterOptions.jsonConversionEventCallback(new JsonConversionEventCallbackImpl());
```

6.10.1.5 Example: Initialize the Reactor JSON Converter

```
// Initialize the JSON converter
if ( reactor.initJsonConverter(jsonConverterOptions, errorInfo) != ReactorReturnCodes.SUCCESS)
{
    System.out.println("Reactor.initJsonConverter() failed: " + errorInfo.toString());
    System.exit(ReactorReturnCodes.FAILURE);
}
```

6.10.2 Interactive Provider and WebSocket Support

For the Interactive Provider to support WebSocket connection requests, you must initialize the Interactive Provider and define **WSocketOpts.protocols**, based on the types of protocol you want to support, as follows:

- To support WebSocket connections for only the RWF sub-protocol, use **BindOptions.wSocketOpts().protocols("rss1.rwf")**.
 - This is the only requirement. For an example of setting **wSocketOpts**, refer to Section 6.10.2.1.
 - For remaining tasks for managing the Interactive Provider, refer to Chapter 4, Building an OMM Interactive Provider.
- To support WebSocket connection requests for both JSON2 and RWF sub-protocols, use **BindOptions.wSocketOpts().protocols("rss1.rwf, rss1.json.v2, tr_json2")**.
- To support WebSocket connection requests only JSON2 sub-protocol, use **BindOptions.wSocketOpts().protocols("rss1.json.v2, tr_json2")**.

For details on **WSocketOpts**, refer to the *Enterprise Transport API Java Edition Developer Guide*.

To support the JSON protocol (either alone, or in tandem with RWF), after initializing the Interactive Provider, you must then perform the following:

- Define the Reactor JSON Converter event callback by using the **JsonConverterOptions.jsonConversionEventCallback()** function. For an example, refer to Section 6.10.2.2.
- Define the **ServiceName** to **ServiceId** callback (using the **JsonConverterOptions.serviceNameToIdCallback()** function). For an example, refer to Section 6.10.2.2.
- Clear and populate a JSON converter options object using the callbacks from the preceding tasks. For an example, refer to Section 6.10.2.3.
- Initialize the Reactor JSON Converter using the **Reactor.initJsonConverter()** function passing in the JSON converter options **ReactorJsonConverterOptions**. For an example, refer to Section 6.10.2.4.
- For remaining tasks on managing the Interactive Provider, refer to Chapter 4, Building an OMM Interactive Provider.

6.10.2.1 Example: Initializing the Publisher to Support WebSocket Connections for RWF Only

To support WebSocket connections for only the RWF sub-protocol, initialize the **Server** (for details, refer to Section 4.3) with `bindOptions.wSocketOpts().protocols("rssl.rwf")`.

```
bindOptions.majorVersion(Codec.majorVersion());
bindOptions.minorVersion(Codec.minorVersion());
bindOptions.protocolType(Codec.protocolType());
bindOptions.serviceName(portNo);
bindOptions.wSocketOpts().protocols("rssl.rwf");
```

6.10.2.2 Example: Defining Reactor JSON Converter Event Callback and ServiceName to ServiceId Callback

```
@Override
public int reactorJsonConversionEventCallback(ReactorJsonConversionEvent jsonConversionEvent)
{
    System.out.println("JSON Conversion error: " + jsonConversionEvent.error().text());

    return ReactorCallbackReturnCodes.SUCCESS;
}

public class ServiceNameIdCallbackImpl implements ReactorServiceNameToIdCallback {

    @Override

    public int reactorServiceNameToIdCallback(ReactorServiceNameToId serviceNameToId,
                                              ReactorServiceNameToIdEvent serviceNameToIdEvent)
    {
        if(directoryHandler.serviceName().equals(serviceNameToId.serviceName()))
        {
            serviceNameToId.serviceId(directoryHandler.serviceId());
            return ReactorReturnCodes.SUCCESS;
        }

        return ReactorReturnCodes.FAILURE;
    }
}
```

6.10.2.3 Example: Clear and Populate a JSON Converter Options Structure with Callback Information

```
ReactorJsonConverterOptions jsonConverterOptions = ReactorFactory.createReactorJsonConverterOptions();

jsonConverterOptions.clear();
jsonConverterOptions.dataDictionary(dictionary);
jsonConverterOptions.serviceNameToIdCallback(new ServiceNameIdCallbackImpl());
jsonConverterOptions.jsonConversionEventCallback(new JsonConversionEventCallbackImpl());
jsonConverterOptions.defaultServiceId(1);
```

6.10.2.4 Example: Initialize the Reactor JSON Converter Using the initJsonConverter() Function

```
if ( reactor.initJsonConverter(jsonConverterOptions, errorInfo) != ReactorReturnCodes.SUCCESS)
{
    System.out.println("Reactor.initJsonConverter() failed: " + errorInfo.toString());
    System.exit(ReactorReturnCodes.FAILURE);
}
```

6.10.3 ReactorJsonConverterOptions

The `ReactorJsonConverterOptions` structure includes the following options:

MEMBER	DESCRIPTION
catchUnknownJsonFids	When converting from JSON to RWF, sets the Enterprise Transport API to catch unknown JSON field IDs. <code>catchUnknownJsonFids</code> is a <code>boolean</code> and defaults to <code>true</code> .
catchUnknownJsonKeys	When converting from JSON to RWF, sets the Enterprise Transport API to catch unknown JSON keys. <code>catchUnknownJsonKeys</code> is a <code>boolean</code> and defaults to <code>false</code> .
closeChannelFromFailure	A <code>boolean</code> that closes the channel if the Reactor fails to parse a JSON message or if the Reactor receives a JSON error message. <code>closeChannelFromFailure</code> defaults to <code>true</code> .
defaultServiceId	If both <code>ServiceName</code> and <code>ServiceID</code> are not set, <code>defaultServiceId</code> specifies a default service ID for requests. <code>defaultServiceId</code> defaults to <code>-1</code> (i.e., not set). <code>defaultServiceId</code> accepts a valid range of <code>0</code> to <code>65535</code> .
jsonExpandedEnumFields	A <code>boolean</code> that expands enumerated values in field entries to their display values for the JSON protocol. <code>jsonExpandedEnumFields</code> defaults to <code>false</code> (do not expand the field).
dataDictionary	Sets the data dictionary (<code>DataDictionary</code>) that Enterprise Transport API uses to initialize the RWF/JSON converter. <code>dataDictionary</code> defaults to <code>null</code> .

Table 89: `ReactorJsonConverterOptions` Class Members

MEMBER	DESCRIPTION
JsonConversionEventCallback	<p>Specifies the callback function (<code>ReactorJsonConversionEventCallback</code>) that receives the <code>ReactorJsonConversionEvent</code> if the JSON converter fails to convert a message.</p> <p><code>JsonConversionEventCallback</code> defaults to <code>null</code>.</p> <ul style="list-style-type: none"> For further details on <code>ReactorJsonConversionEventCallback</code>, refer to Section 6.10.4. For further details on <code>ReactorJsonConversionEvent</code>, refer to Section 6.10.7.
serviceNameToIdCallback	<p>Specifies the callback function (<code>ReactorServiceNameToIdCallback</code>) that handles conversion of the <code>ServiceName</code> to <code>ServiceId</code>.</p> <p><code>serviceNameToIdCallback</code> defaults to <code>null</code>.</p> <p>For further details on <code>ReactorServiceNameToIdCallback</code>, refer to Section 6.10.5.</p>
userSpec	<p>Specifies a user-defined pointer which is retrieved in the callback function.</p> <p><code>userSpec</code> is an object type and defaults to <code>null</code>.</p>

Table 89: `ReactorJsonConverterOptions` Class Members (Continued)

6.10.4 `ReactorJsonConversionEventCallback` Function

The `ReactorJsonConversionEventCallback` function communicates conversion information when the JSON converter fails to convert JSON to RWF messages by providing an `ReactorJsonConversionEvent` object to the application. For further details on `ReactorJsonConversionEvent`, refer to Section 6.10.7.

6.10.5 ReactorServiceNameToIdCallback Function

`ReactorServiceNameToIdCallback` calls back to the application to translate a `ServiceName` to `ServiceId` by application by providing an `ReactorServiceNameToIdEvent`. For further details on `ReactorServiceNameToIdEvent`, refer to Section 6.10.6.

- If `ReactorServiceNameToIdCallback` succeeds, it returns `ReactorReturnCodes.SUCCESS`.
- If `ReactorServiceNameToIdCallback` fails, it returns `ReactorReturnCodes.FAILURE`.

PARAMETER	DESCRIPTION
ReactorServiceNameTold	Carries the <code>serviceName</code> and <code>serviceId</code> fields. The application populates the <code>serviceId</code> field by looking up the appropriate <code>serviceName</code> .
ReactorServiceNameToldEvent	<code>ReactorServiceNameToIdEvent</code> occurs when the Reactor needs to convert from a <code>serviceName</code> to a <code>serviceId</code> .

Table 90: `ReactorServiceNameToIdCallback` Parameters

6.10.6 ReactorServiceNameToIdEvent Class

The `ReactorServiceNameToIdEvent` class includes the following options:

MEMBER	DESCRIPTION
userSpecObj	Specifies a user-defined reference provided when specifying the callback for the <code>ReactorServiceNameToIdEvent</code> event. <code>userSpecObj</code> is an object type and defaults to <code>null</code> .

Table 91: `ReactorServiceNameToIdEvent` Class Members

6.10.7 ReactorJsonConversionEvent Class

The `ReactorJsonConversionEvent` class includes the following options:

MEMBER	DESCRIPTION
userSpec	Specifies a user-defined reference provided when specifying the callback for the <code>ReactorServiceNameToIdEvent</code> event. <code>userSpec</code> is an object type and defaults to <code>null</code> .
error	Contains any error information (<code>Error</code>) associated with a JSON conversion.

Table 92: `ReactorJsonConversionEvent` Class Members

6.11 Reactor Utility Methods

The Transport API Reactor provides several additional utility functions. These functions can be used to query more detailed information for a specific connection or change certain **ReactorChannel** parameters during run-time. These functions are described in the following Section 6.11.1 - Section 6.11.3.

6.11.1 General Reactor Utility Methods

METHOD NAME	DESCRIPTION
info	Allows the application to query ReactorChannel negotiated parameters and settings and retrieve all current settings. This includes maxFragmentSize and negotiated compression information as well as many other values. For a full list of available settings, refer to the ReactorChannelInfo object defined in Section 6.11.2. This method calls the Enterprise Transport API Channel.info method which has its use and return values described in the Enterprise Transport API Java Edition <i>Developers Guide</i> .
Channel.ioctl	Allows the application to change various settings associated with the ReactorChannel . The available options are defined in Section 6.11.3. This method calls the Channel.ioctl method which has its use and return values described in the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 93: Reactor Utility Methods

6.11.2 ReactorChannelInfo Class Members

The following table describes the values available to the user through using the **ReactorChannel.info** method. This information is returned as part of the **ReactorChannelInfo** object.

CLASS MEMBER	DESCRIPTION
channelInfo	Returns the underlying Channel information. This includes maxFragmentSize , number of output buffers, compression information, and more. The ChannelInfo method object is fully described in the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 94: ReactorChannelInfo Class Members

6.11.3 ReactorChannel.ioctl Option Values

There are currently no **Reactor** or **ReactorChannel** specific codes for use with the **ioctl** method. Reactor-specific codes may be added in the future. The application can still use any of the codes allowed with **ioctl**, which are documented in the Enterprise Transport API Java Edition *Developers Guide*.

6.11.4 Debugging for Reactor

The **Reactor** class provides the following methods for controlling debugging process.

METHOD	DESCRIPTION
void enableDebuggingLevel(int level)	Enables the provided debugging level. For the list of available debugging levels, see Section 6.2.1.5.

METHOD	DESCRIPTION
void disableDebuggingLevel(int level)	Disables the provided debugging level.
int debuggingLevels()	Returns the debugging levels currently set for this Reactor instance.
byte[] getDebuggingInfo()	<p>Provides access to the messages debugged up to this point in case the underlying debugger stream is an instance of ByteArrayOutputStream (which is the case when, e.g., no output stream was provided in the ReactorDebuggerOptions while creating the Reactor instance). Returns a byte array that contains debugging messages (up to a certain capacity) currently written from the beginning of debugging or since the last call to this method.</p> <p>In case debugging is not enabled at the point when this method is called, one of the following can be returned:</p> <ul style="list-style-type: none"> • Null in case the user has provided a debug output stream that is not an instance of ByteArrayOutputStream. • Otherwise, a byte array; if debugging was at some point enabled and this method has not been priorly called, the array will contain the previously logged messages.

Table 95: Reactor Methods for Debugging Handling

7 Consuming Data from the Cloud

7.1 Overview

You can use the Enterprise Transport API to consume data from a cloud-based Refinitiv Real-Time Advanced Distribution Server. The API interacts with cloud-based servers using the following workflows:

- Credential Management (for details, refer to Section 7.3)
- Service Discovery (for details, refer to Section 7.6)
- Consuming Market Data (for details, refer to Section 7.7)
- Login Reissue (for details, refer to Section 7.4.3)

There are two versions of login credentials for the Refinitiv Data Platform.

- Version 1 Authentication also known as “V1 auth”, “OAuthPasswordGrant” or “V1 Password Credentials”: Uses the OAuth2.0 Password grant or Refresh Token grant. Requires a Machine Account consisting of username and password; also requires a client ID generated by the Refinitiv **AppGenerator**. For details, refer to Section 7.5.
- Version 2 Authentication also known as “V2 auth”, “OAuthClientCredentials” or “V2 Client Credentials”: Uses OAuth2.0 Client Credentials grant to obtain an access token. Requires a Service Account consisting of client ID and client Secret. For details, refer to Section 7.5.

NOTE: Version 2 Authentication is available as an **Early Access** feature to API developers to preview changes required to use this new authentication mechanism. Please note that the ability to setup Service Accounts to use this authentication is forthcoming.

The Enterprise Transport API will determine which authentication version to use based on the inputs. By default, for cloud connections the Enterprise Transport API connects to a server in the **us-east-1** cloud location.

For further details on Refinitiv Real-Time as it functions in the cloud, refer to the *Refinitiv Real-Time — Optimized: Installation and Configuration for Client Use*.

7.2 Encrypted Connections

When connecting to a Refinitiv Real-Time Advanced Distribution Server in the cloud, you must use an encrypted connection type (for details on connection types, refer to the *ETA Java Developer Guide*).

7.3 Credential Management

By default, the Enterprise Transport API will store all credential information. In order to use secure credential storage, a callback function can be specified by the user. If a callback function is specified, credentials are not stored in API; instead, application is called back whenever credentials are required.

When configuring the **ReactorChannel**, if **ReactorOAuthCredential.ReactorOAuthCredentialEventCallback** is specified, the API will call the user back whenever credentials are required. This callback must call **Reactor.submitOAuthCredentialRenewal** to submit the updated credentials.

7.4 Version 1 Authentication Using oAuth Password and Refresh_Token

7.4.1 Client_ID (AppKey)

To connect to Refinitiv Real-Time - Optimized infrastructure, the Enterprise Transport API requires a **Client_ID**, and optionally can include a client secret. **Client_IDs** are generated using **AppGenerator**, which refers to the **Client_ID** as an AppKey. Each user must obtain their unique **Client_ID** using the machine account email sent by Refinitiv, which includes a link to **AppGenerator**. Keep your **Client_ID** private: do not share **Client_IDs**.

- For further details on generating this ID, refer to the *Refinitiv Real-Time - Optimized: Installation and Configuration for Client Use* document. Each **Client_ID** is unique: do not share it with others.
- For details on how OAuth uses a Client Secret with a Client ID and their relationship, refer to OAuth documentation at: the following URL: <https://www.oauth.com/oauth2-servers/client-registration/client-id-secret/>.

7.4.2 Obtaining Initial Access and Refresh Tokens

To obtain an access token, the RTSDK API sends its username, **Client_ID** (from **ConsumerRole** as described in Section 6.3.2.1), and password (defined in the Login Domain, as described in Section 8.3) in a single message to the Refinitiv Data Platform. You must configure these details (in the **OmmConsumerConfig** object) before executing a calls connect (for details on the **Reactor.connect** method, refer to Section 6.4.1.1).

In response, the Refinitiv Data Platform sends an access token, its expiration timeout (by default: 300 seconds), and a refresh token for use in the login reissue process (for details on the expiration timeout and login reissue process, refer to Section 7.4.3). The API must obtain an access token before executing a service discovery or obtaining market data.

The following diagram illustrates the process by which the RTSDK API obtains its tokens:




Figure 9. Obtaining an Authentication Token

7.4.3 Refreshing the Access Token and Sending a Login Reissue

In response to the API's token request, the Refinitiv Data Platform sends an access token and a refresh token, both with associated expiration timeouts which set the length of time for which the token is valid. If the Refinitiv Real-Time Advanced Distribution Server does not receive a new access token before the end of the expiration timeout, the Refinitiv Real-Time Advanced Distribution Server sends a login close status message and closes the connection.

To create a seamless experience for API users, the API sends the refresh token to proactively obtain a new access token prior to the published expiration timeout. The Enterprise Transport API calculates the time at which it requests a new access token by multiplying the token's published timeout by 4/5 (i.e., **0.8**). Thus, if the default is 300 seconds, the API requests a new access token after 240 seconds. You can configure this reissue ratio using `ReactorOptions.tokenReissueRatio` (for details, refer to Section 6.2.1.2).

In response to receiving a refresh token, the Refinitiv Data Platform sends a new access token with an associated timeout to the API. After receiving the new access token from the Refinitiv Data Platform, the API renews its connection by sending a Login Reissue with the new access token to the Refinitiv Real-Time Advanced Distribution Server. The process of renewing the access token and refreshing the Refinitiv Real-Time Advanced Distribution Server connection via a Login Reissue continues until the refresh token itself expires (which can take several hours or days). When using a `grant_type` of `refresh_token`, if the value for `expires_in` does not match the `expires_in` received from when the API obtained the `refresh_token` (i.e., when `grant_type` was `password`), this is an indication that the `refresh_token` is about to expire. In this case, the API will obtain a new set of both refresh and access tokens as described in Section 7.4.2.

The login reissue process is illustrated in the following diagram:




Figure 10. Login Reissue

7.4.4 Session Management per User Credential

Prior to Version 3.6.0, the Enterprise Transport API would manage tokens separately across each channel, even when using the same Username, Client ID, and password credentials. So that each channel had a unique pair of access and refresh tokens. API would manage each channel distinct from the others.

As of Version 3.6.0, the Enterprise Transport API connects to the Refinitiv Data Platform once and reuses the same access and refresh tokens for all channels. The Enterprise Transport API supports up to, but no more than, 5 channels per OAuth credential set.

7.5 Version 2 Authentication Using oAuth Client Credentials

Version 2 OAuth Client Credentials requires a client ID and client secret, or private JWK for JWT, or a client ID and private client JWK for OAuth Client Credentials with JWT. Version 2 will only generate an Access Token, not both Access and Refresh Token.

Once connected to Refinitiv Real-Time — Optimized Advanced Distribution Server, there is no need to renew the Access Token. The login session to the Advanced Distribution Server will remain valid until the consumer disconnects or is disconnected from Refinitiv Real-Time — Optimized. The API will only re-request an Access Token in the following cases:

- When the consumer disconnects and goes into a reconnection state.
- If the `reactorChannel` stays in reconnection long enough to get close to the expiry time of the Access Token.

Due to the above changes, credentials are managed independently per reactor channel. Channels do not share credentials.

7.5.1 Configuring and Managing Version 2 Credentials

The client ID and client secret or private JWK must be set on the `RsslReactorOAuthCredential` as described in Section 6.9.2.1 of the *Enterprise Transport API Java Edition Value Added Developers Guide*. The `ReactorI` will handle the credentials the same way as Version 1, with a `IRsslReactorOAuthCredentialEvent` callback for credentials if the user does not wish for the `ReactorI` to store them.

7.5.1.1 JWT Credentials Handling

Version 2 OAuth Client Credentials with JWT requires a JWK public/private pair to be generated and registered with Refinitiv via the Platform Admin UI. The API will use a private JWK to create and sign a JWT request, which will be sent to retrieve an access token. The JWK will be handled by the API the exact same way as a client secret above. For more information about the Platform Admin UI, refer to the Refinitiv Real-Time — Optimized documentation in the Refinitiv Developers portal.

NOTE: Follow best practices for securely storing and retrieving JWK.

7.5.2 Version 2 OAuth Client Credentials Token Lifespan

Unlike Version 1, Version 2 will only produce a single Access Token, which will be valid for the length of the entire `expires_in` field in the token. This Access Token is used by the API to perform service discovery, and to connect to Refinitiv Real-Time — Optimized.

Once connected, the API does not need to periodically renew a token.

The API will re-request a token on reconnect, and will use that token for all reconnect attempts until a short time prior to expiry. At that time, the API will get a new token for reconnection use.

7.6 Service Discovery

After obtaining a token (for details, refer to Section 7.4.2), the Enterprise Transport API can perform a service discovery against the Refinitiv Data Platform to obtain connection details for the Refinitiv Real-Time — Optimized. The Enterprise Transport API Java Edition uses the `Reactor.queryServiceDiscovery` method to submit a service discovery (refer to Section 6.2.1 for a description of this reactor method).

In response to a service discovery, the Refinitiv Data Platform returns transport and data format protocols and a list of hosts and associated ports for the requested service(s) (i.e., a Refinitiv Real-Time Advanced Distribution Server running in the cloud or endpoint). Refinitiv provides multiple cloud locations based on region, which is significant in how the Enterprise Transport API chooses the IP address and port to use when connecting to the cloud.

From the list sent by the Refinitiv Data Platform, the Enterprise Transport API identifies a Refinitiv Real-Time — Optimized endpoint with built-in resiliency whose regional location matches the API's location setting in `ReactorConnectInfo` (for details, refer to Section 6.4.1.3). If you do not specify a location, the Enterprise Transport API defaults to the `us-east-1` cloud location. An endpoint with built-in resiliency lists multiple locations in its location field (e.g., `location: [us-east-1a, us-east-1b]`). If multiple endpoints are configured for failover, the Enterprise Transport API chooses to connect to the first endpoint listed.





Figure 11. Service Discovery

7.7 Consuming Market Data

After obtaining its login token (for details, refer to Section 7.4.2) and running a service discovery (for details, refer to Section 7.6), the API can connect to the Refinitiv Real-Time Advanced Distribution Server in the cloud and obtain market data. While consuming market data, the API must periodically renew its token via the login reissue workflow (for details, refer to Section 7.4.3).



7.8 HTTP Error Handling for Reactor Token Reissues

The Enterprise Transport API supports handling for the following HTTP error codes from the API gateway:

- 300 Errors:
 - Perform URL redirect for 301, 302, 307 and 308 error codes
 - Retry the request to the API gateway for all other error codes
- 400 Errors:
 - For Version 1 authentication, retry with username and password for error codes 400 and 401
 - Stop retry the request for error codes 403, 404, 410, and 451
 - Retry the request to the API gateway for all other error codes
- 500 Errors:
 - Retry the request to the API gateway for all error codes

7.9 Cloud Connection Use Cases

You can connect to the cloud and consume data according to the following use cases:

- Start to finish session management using Reactor watchlist (for details, refer to Section 7.9.1)
- Session management using Reactor with watchlist disabled (for details, refer to Section 7.9.2)
- Explicit service discovery use case (for details, refer to Section 7.9.3)

7.9.1 Session Management Use Case

In this use case, when using Enterprise Transport API Reactor with watchlist enabled in conjunction with session management, the API manages the entire connection from start to finish. To enable session management, set `EnableSessionManagement` in `ReactorConnectInfo`.

The API exhibits the following behavior when enabling both session management and watchlist features:

1. Obtains a token and renews access token as needed (according to the details in Section 7.4).
2. Performs an implicit service discovery and chooses an endpoint based on specified or defaulted location (us-east-1) to connect to (according to the details in Section 7.6).
3. Consumes market data from either discovered or specified endpoint (according to the details in Section 7.7).
4. Manages login reissues for Version 1 authentication when needed on a cyclical basis (according to the details in Section 7.4.3).

Possible ways to use session management with watchlist enabled include:

- By default, a default location is used to do implicit service discovery as detailed above and a LSEG resilient endpoint is automatically chosen for connectivity as detailed above. See Section 7.5 for details on service discovery.
- Application may specify a location to override default location. An LSEG resilient endpoint is automatically chosen from the specified region.
- Application may also choose to not consider results of automatic implicit service discovery by setting host and port to connect to. In this case, service discovery still occurs, however, results are ignored. Host and port information must be set in `ReactorConnectInfo` instance from `ReactorConnectOptions.ConnectionList` list.

7.9.2 Disabling the Watchlist

When connecting to a Refinitiv Real-Time Advanced Distribution Server in the cloud with the watchlist disabled (the default), the API:

- Obtains a token (according to the details in Section 7.4.2)
- If needed, queries service discovery (according to the details in Section 7.6)

The Reactor initially handles the RDM Login request, with the application handling subsequent Login Reissues using renewed access tokens.

To support this use case, you must configure session management (i.e., in `ReactorConnectInfo` objects, set `enableSessionManagement`).

7.9.3 Query Service Discovery

Application has the option to do a service discovery, parse the results, and choose an endpoint to pass into API. Depending on whether or not the watchlist is enabled, API will behave according to use cases already described in this section to manage session:

1. Obtains a token (according to the details in Section 7.4.2).
2. Queries service discovery (according to the details in Section 7.6).

7.10 Logging of Authentication and Service Discovery Interaction

If needed, you can log the interactions with the Refinitiv Data Platform. To enable logging, you must activate the logging section in the `build.gradle` file in the `.../PackageDirectory/Ema/Examples` directory, as described in the *RTSDK Java Edition Installation Guide*.

You can configure the location of the logging file (`logging.properties`), by editing the `java.util.logging.config.file` parameter.

To turn on logging, add the following text to the `logging.properties` file:

```
com.refinitiv.eta.valueadd.reactor.RestReactor.level=FINEST
java.util.logging.ConsoleHandler.level=FINEST
```

7.10.1 Logged Request Information

With logging turned on in the fashion mentioned in Section 7.10, the Enterprise Transport API writes the following request information in the log:

```
Request:
- Time stamp
- The Name of the class and method that made the request
- Request method
- URI
- Request headers
- Proxy information (if used)
- Body of request as set of pairs parameter_name: parameter_value
```

NOTE: If the request contains parameters `password`, `newPassword`, or `client_secret`, the Enterprise Transport API uses a placeholder instead of the real value of the respective parameter (thus indicating that the value was present).

7.10.2 Logged Response Information

With logging turned on in the fashion mentioned in Section 7.10, the Enterprise Transport API writes the following response information in the log:

```
Response:
- Time stamp
- The Name of the class and method that received the response
- Response status code
- Response headers
- Body of response in string format
```

8 Administration Domain Models Detailed View

8.1 Concepts

Administration Domain Model Representations are RDM-specific representations of OMM administrative domain models. This Value Added Component contains classes and interfaces that represent messages within the Login, Source Directory, and Dictionary domains (discussed in Table 96). This component also handles all encoding and decoding functionality for these domain models, so the application needs only to manipulate the message's object members to send or receive content. Such functionality significantly reduces the amount of code an application needs to interact with OMM devices (i.e., Refinitiv Real-Time Distribution System infrastructure), and also ensures that encoding/decoding for these domain models follow OMM-specified formatting rules. Applications can use this Value Added Component directly to help with encoding, decoding, and representation of these domain models.

Where possible, the members of an Administration Domain Model Representation are represented in the class with the same **Data Type** that is specified for the element by the domain model. In cases where multiple elements are part of a more complex container such as a **Map** or **ElementList**, the elements are represented with Java JDK collections.

The Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide* defines and describes all domain-specific behaviors, usage, and details.

DOMAIN	PURPOSE
Dictionary	<p>Provides dictionaries that may be needed when decoding data. Though use of the Dictionary domain is optional, Refinitiv recommends that provider applications support the domain's use.</p> <p>The Dictionary domain is considered an administrative domain. Many Refinitiv components require this content and expect it to follow the domain model definition.</p> <p>For further details refer to Section 8.5.</p>
Login	<p>Authenticates users and advertises/requests features that are not specific to a particular domain. Use of and support for this domain is required for all OMM applications.</p> <p>Login is considered an administrative domain. Many Refinitiv components require this content and expect it to conform to the domain model definition.</p> <p>For further details refer to Section 8.3.</p>
Source Directory	<p>Advertises information about available services and their state, quality of service, and capabilities. This domain also conveys any group status and group merge information.</p> <p>Interactive and non-interactive provider applications require support for this domain. Refinitiv strongly recommends that consumers request this domain.</p> <p>Source Directory is considered an administrative domain, and many Refinitiv components expect this content and require it to conform to the domain model definition.</p> <p>For further details, refer to Section 8.4.</p>

Table 96: Domains Representations in the Administration Domain Model Value Added Component

8.2 Message Base

MsgBase is the root interface for all Administration Domain Model Representation interfaces. It provides methods for stream identification as well as methods that are common for all domain representations.

8.2.1 Message Base Members

The **MsgBase** interface includes the following members and methods:

MEMBER	DESCRIPTION
streamId	Required. A unique signed-integer identifier associated with all messages flowing in the stream. <ul style="list-style-type: none"> • Positive values indicate a consumer-instantiated stream, typically via a request message. • Negative values indicate a provider-instantiated stream, often associated with Non-Interactive Providers.

Table 97: **MsgBase** Members

8.2.2 Message Base Method

METHOD	DESCRIPTION
clear()	Clears the object for reuse.

Table 98: **MsgBase** Method

8.2.3 RDM Message Types

The following table provides a reference mapping between the administrative domain type and the domain representations provided in this component.

DOMAIN TYPE	DOMAIN REPRESENTATIONS MESSAGE TYPE	DOMAIN REPRESENTATION INTERFACE
LOGIN (LoginMsg) Refer to Section 8.3	LoginMsgType.REQUEST	LoginRequest
	LoginMsgType.REFRESH	LoginRefresh
	LoginMsgType.STATUS	LoginStatus
	LoginMsgType.CLOSE	LoginClose
	LoginMsgType.CONSUMER_CONNECTION_STATUS	LoginConsumerConnectionStatus
	LoginMsgType.RTT	LoginRTT
SOURCE (DirectoryMsg) Refer to Section 8.4	DirectoryMsgType.REQUEST	DirectoryRequest
	DirectoryMsgType.REFRESH	DirectoryRefresh
	DirectoryMsgType.UPDATE	DirectoryUpdate
	DirectoryMsgType.STATUS	DirectoryStatus
	DirectoryMsgType.CLOSE	DirectoryClose
	DirectoryMsgType.CONSUMER_STATUS	DirectoryConsumerStatus
DICTIONARY (DictionaryMsg) Refer to Section 8.5	DictionaryMsgType.REQUEST	DictionaryRequest
	DictionaryMsgType.REFRESH	DictionaryRefresh
	DictionaryMsgType.STATUS	DictionaryStatus
	DictionaryMsgType.CLOSE	DictionaryClose

Table 99: Domain Representations Message Types

8.3 RDM Login Domain

The Login domain registers (or authenticates) a user with the system, after which the user can request¹, post², or provide³ OMM content. A Login request may also be used to authenticate a user with the system.

- A consumer application must log into the system before it can request or post content.
- A non-interactive provider (NIP) application must log into the system before providing content. An interactive provider application must handle login requests and provide login response messages, possibly using the Data Access Control System to authenticate users.

Section 8.3.1 - Section 8.3.12 detail the layout and use of each message interface in the Login portion of the Administration Domain Message Component.

8.3.1 Login Request

A **Login Request** message is encoded and sent by OMM consumer and non-interactive provider applications. This message registers a user with the system. After receiving a successful login response, applications can then begin consuming or providing additional content. An OMM provider can use the login request information to authenticate users with the Data Access Control System.

The **LoginRequest** represents all members of a login request message and allows for simplified use in OMM applications that leverage RDMS. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.3.1.1 Login Request Members

MEMBER	DESCRIPTION
	Optional. Contains additional login attribute information. If present, a flags value of LoginRequestFlags.HAS_ATTRIB should be specified. For further details, refer to Section 8.3.9.1.
authenticationExtended	Optional. If present, a flags value of LoginRequestFlags.HAS_AUTHENTICATION_EXTENDED should be specified. When populated, authenticationExtended contains additional content that will be passed to the token authenticator as an additional means to verifying a user's identity.
downloadConnectionConfig	Optional. If present, a flags value of LoginRequestFlags.HAS_DOWNLOAD_CONN_CONFIG should be specified. If absent, a default value of 0 is assumed. Enabling this option allows the application to download information about other providers on the network. You can use such downloaded information to load balance connections across multiple providers. <ul style="list-style-type: none"> • 1: Indicates that the user wants to download connection configuration information. • 0: Indicates that the user does not want to download connection information.
flags	Required. Indicates presence of optional login request members. For details, refer to Section 8.3.1.2.

Table 100: LoginRequest Members

-
1. Consumer applications can request content after logging into the system.
 2. Consumer applications can post content (similar to contributions or unmanaged publications) after logging into the system.
 3. Non-interactive provider applications.

MEMBER	DESCRIPTION
instanceId	<p>Optional. If present, a <code>flags</code> value of <code>LoginRequestFlags.HAS_INSTANCE_ID</code> should be specified.</p> <p>You can use the <code>instanceId</code> to differentiate applications running on the same machine. However, because <code>instanceId</code> is set by the user logging into the system, it does not guarantee uniqueness across different applications on the same machine.</p>
password	<p>Optional. If present, a <code>flags</code> value of <code>LoginRequestFlags.HAS_PASSWORD</code> should be specified. Sets the password for logging into the system.</p>
rdmMsgBase	<p>Required. Specifies the login message type (i.e., <code>LoginMsgType.REQUEST</code> for the login request).</p>
role	<p>Optional. If present, a <code>flags</code> value of <code>LoginRequestFlags.HAS_ROLE</code> should be specified. If absent, a default value of <code>Login.Role.CONSUMER</code> is assumed.</p> <p>Indicates the role of the application logging onto the system.</p> <ul style="list-style-type: none"> • 0: <code>Login.Role.CONSUMER</code>, indicates application is a consumer. • 1: <code>Login.Role.PROVIDER</code>, indicates application is a provider.
userName	<p>Required. Populate this member with the username, email address, or user token based on the <code>userNameType</code> specification.</p> <p>If you initialize <code>LoginRequest</code> using <code>initDefaultRequest</code>, it uses the name of the user currently logged into the system on which the application runs.</p>
userNameType	<p>Optional. If present, a <code>flags</code> value of <code>LoginRequestFlags.HAS_USERNAME_TYPE</code> should be specified. If absent, a default value of <code>Login.UserIdTypes.NAME</code> is assumed.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • <code>Login.UserIdTypes.NAME = 1</code> • <code>Login.UserIdTypes.EMAIL_ADDRESS = 2</code> • <code>Login.UserIdTypes.TOKEN = 3</code> • <code>Login.UserIdTypes.COOKIE = 4</code> • <code>Login.UserIdTypes.AUTHN_TOKEN==5</code> <p>A type of <code>Login.UserIdTypes.NAME</code> typically corresponds to a Data Access Control System user name and can be used to authenticate and permission a user.</p> <p><code>Login.UserIdTypes.TOKEN</code> is specified when using the AAA ('triple A') API. The user token is retrieved from the Authentication Manager application. To validate users, a provider application passes this user token to the AAA Gateway. This type of token periodically changes: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to documentation specific to the AAA API.</p> <p><code>Login.UserIdTypes.AUTHN_TOKEN</code> is specified when using Refinitiv Real-Time Distribution System Authentication. The authentication token should be specified in the <code>userName</code> member. This type of token can periodically change: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i>.^a</p>

Table 100: LoginRequest Members (Continued)

a. For further details on Refinitiv Real-Time Distribution System Authentication, refer to the *Refinitiv Real-Time Distribution System Authentication User Manual*, accessible on [MyRefinitiv](#) in the Data Access Control System product documentation set.

8.3.1.2 Login Request Flag Enumeration Values

FLAG ENUMERATION	MEANING
LoginRequestFlags.HAS_ATTRIB	Indicates the presence of .
LoginRequestFlags.HAS_AUTHN_EXTENDED	Indicates the presence of authenticationExtended .
LoginRequestFlags.HAS_DOWNLOAD_CONN_CONFIG	Indicates the presence of downloadConnectionConfig . If absent, a value of 0 should be assumed.
LoginRequestFlags.HAS_INSTANCE_ID	Indicates the presence of instanceId .
LoginRequestFlags.HAS_PASSWORD	Indicates the presence of password .
LoginRequestFlags.HAS_ROLE	Indicates the presence of role . If absent, a role of Login.Role.CONS is assumed.
LoginRequestFlags.HAS_USERNAME_TYPE	Indicates the presence of userNameType . If not present, a userNameType of Login.UserIdTypes.NAME should be assumed.
LoginRequestFlags.NO_REFRESH	Indicates that the consumer application does not require a login refresh for this request. This typically occurs when resuming a stream or changing a AAA token. In some instances, a provider can still deliver a refresh message, however if such a message is not explicitly asked for by the consumer, it is considered unsolicited.
LoginRequestFlags.PAUSE_ALL	Indicates that the consumer wants to pause all streams associated with the logged in user. For more information on pause and resume behavior, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 101: LoginRequest Flags

8.3.1.3 Login Request Utility Method

METHOD NAME	DESCRIPTION
initDefaultRequest	Clears a LoginRequest object and populates userName , position , applicationId , and applicationName with default values.

Table 102: LoginRequest Utility Method

8.3.2 Login Refresh

A **Login Refresh** message is encoded and sent by an OMM interactive provider application and responds to a Login Request message. A login refresh message indicates that the user's Login is accepted. A provider can use information from the login request to authenticate users with the Data Access Control System. After authentication, a refresh message is sent to convey that the login was accepted. If the login is rejected, a login status message should be sent as described in Section 8.3.3.

The **LoginRefresh** represents all members of a login refresh message and allows for simplified use in OMM applications that leverage RDMS. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.3.2.1 Login Refresh Members

MEMBER	DESCRIPTION
	Optional. Contains additional login attribute information. If present, a flags value of LoginRefreshFlags.HAS_ATTRIB should be specified. For details, refer to Section 8.3.9.1.
authenticationErrorCode	Optional. If present, a flags value of LoginRefreshFlags.HAS_AUTHN_ERROR_CODE should be specified. authenticationErrorCode is specific to a Refinitiv Real-Time Distribution System Authentication environment, where 0 indicates an error-free condition. For further information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i> . ^a
authenticationErrorText	Optional. If present, a flags value of LoginRefreshFlags.HAS_AUTHN_ERROR_TEXT should be specified. authenticationErrorText specifies any error text that accompanies an authenticationErrorCode . For further information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i> . ^a
authenticationExtendedResp	Optional. If present, a flags value of LoginRefreshFlags.HAS_AUTHN_EXTENDED_RESP should be specified. authenticationExtendedResp contains additional, customer-defined data associated with the authentication token sent in the original request. For further information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i> . ^a
authenticationTTReissue	Optional. If present, a flags value of LoginRefreshFlags.HAS_AUTHN_TT_REISSUE should be specified. Indicates when a new authentication token needs to be reissued (in UNIX Epoch time). For more information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i> . ^a
connectionConfig	Optional. Indicates the connection configuration that the consumer uses for its standby servers when setup for Warm Standby. If present, a flags value of LoginRefreshFlags.HAS_CONN_CONFIG should be specified.
features	Optional. Indicates a set of features supported by the provider of the login refresh message. If present, a flags value of LoginRefreshFlags.HAS_FEATURES should be specified. For details, refer to Section 8.3.2.3.
flags	Required. Indicate the presence of optional login refresh members. For details, see Section 8.3.2.2.
rdmMsgBase	Required. Specifies the login message type (i.e., LoginMsgType.REFRESH for login refresh).

Table 103: LoginRefresh Members

MEMBER	DESCRIPTION
sequenceNumber	Optional. A user-specified, item-level sequence number which can be used by the application for sequencing messages within this stream. If present, a flags value of LoginRefreshFlags.HAS_SEQ_NUM should be specified.
State	Required. Indicates the state of the login stream. Defaults to a streamState of StreamStates.OPEN and a dataState of DataStates.OK . For more information on State , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
userName	Optional. If present, a flags value of LoginRefreshFlags.HAS_USERNAME should be specified. Contains content appropriate to the corresponding userNameType specification. If populated, this should match the userName contained in the login request.
userNameType	Optional. If present, a flags value of LoginRefreshFlags.HAS_USERNAME_TYPE should be specified. If absent, a default value of Login.UserIdTypes.NAME is assumed. Possible values: <ul style="list-style-type: none"> • Login.UserIdTypes.NAME = 1 • Login.UserIdTypes.EMAIL_ADDRESS = 2 • Login.UserIdTypes.TOKEN = 3 • Login.UserIdTypes.COOKIE==4 • Login.UserIdTypes.AUTHN_TOKEN==5 A type of Login.UserIdTypes.NAME typically corresponds to a Data Access Control System user name and can be used to authenticate and permission a user. Login.UserIdTypes.TOKEN is specified when using the AAA ('triple A') API. The user token is retrieved from the Authentication Manager application. To validate users, a provider application passes this user token to the AAA Gateway. This type of token periodically changes: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to documentation specific to the AAA API. Login.UserIdTypes.AUTHN_TOKEN is specified when using Refinitiv Real-Time Distribution System Authentication. The authentication token should be specified in the userName member. This type of token can periodically change: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i> . ^a

Table 103: LoginRefresh Members(Continued)

a. For further details on Refinitiv Real-Time Distribution System Authentication, refer to the *Refinitiv Real-Time Distribution System Authentication User Manual*, accessible on [MyRefinitiv](#) in the Data Access Control System product documentation set.

8.3.2.2 Login Refresh Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
<code>LoginRefreshFlags.CLEAR_CACHE</code>	Indicates to clear stored payload information associated with the login stream. This might occur if some portion of data is known to be invalid.
<code>LoginRefreshFlags.HAS_ATTRIB</code>	Indicates the presence of .
<code>LoginRefreshFlags.HAS_AUTHN_ERROR_CODE</code>	Indicates the presence of authenticationErrorCode .
<code>LoginRefreshFlags.HAS_AUTHN_ERROR_TEXT</code>	Indicates the presence of authenticationErrorText .
<code>LoginRefreshFlags.HAS_AUTHN_EXTENDED_RESP</code>	Indicates the presence of authenticationExtendedResp .

Table 104: LoginRefresh Flags

FLAG ENUMERATION	DESCRIPTION
LoginRefreshFlags.HAS_AUTHN_TT_REISSUE	Indicates the presence of authenticationTTReissue .
LoginRefreshFlags.HAS_CONN_CONFIG	Indicates the presence of connection configuration information used with warm standby functionality.
LoginRefreshFlags.HAS_FEATURES	Indicates the presence of features . If absent, a value of 0 is assumed.
LoginRefreshFlags.HAS_SEQ_NUM	Indicates the presence of sequenceNumber .
LoginRefreshFlags.HAS_USERNAME	Indicates the presence of userName .
LoginRefreshFlags.HAS_USERNAME_TYPE	Indicates the presence of userNameType . If absent, a userNameType of Login.UserIdTypes.NAME should be assumed.
LoginRefreshFlags.SOLICITED	<ul style="list-style-type: none"> If present, this flag indicates that the login refresh is solicited (e.g., it is in response to a request). If this flag is absent, this refresh is unsolicited.

Table 104: LoginRefresh Flags (Continued)

8.3.2.3 Login Support Feature Set Members

For detailed information on posting, batch requesting, dynamic view use, and 'pause and resume,' refer to the *Transport API Java Edition Developers Guide*.

MEMBER	DESCRIPTION
flags	Required. Indicates the presence of optional login refresh members. For further flag details, refer to Section 8.3.2.4.
supportBatchCloses	Optional. Indicates whether the provider supports batch close functionality. <ul style="list-style-type: none"> • 1: The provider supports batch closing. • 0: The provider does not support batch reissuing. If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_BATCH_CLOSES should be specified. If absent, a default value of 0 is assumed.
supportBatchReissues	Optional. Indicates whether the provider supports batch reissue functionality. <ul style="list-style-type: none"> • 1: The provider supports batch reissuing. • 0: The provider does not support batch reissuing. If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_BATCH_REISSUES should be specified. If absent, a default value of 0 is assumed.
supportBatchRequests	Optional. Indicates whether the provider supports batch request functionality, which allows a consumer to specify multiple items, all with matching attributes, in the same request message. <ul style="list-style-type: none"> • 1: The provider supports batch requesting. • 0: The provider does not support batch requesting. If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_BATCH_REQUESTS should be specified. If absent, a default value of 0 is assumed.
supportEnhancedSymbolList	Optional. Indicates whether the provider supports enhanced symbol list features: <ul style="list-style-type: none"> • 1: The provider supports enhanced symbol list features. • 0: The provider does not support enhanced symbol list features. If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_ENH_SL should be specified. If absent, a default value of 0 is assumed.
supportOptimizedPauseResume	Optional. Indicates whether the provider supports the optimized pause and resume feature. Optimized pause and resume can pause/resume individual item streams or all item streams by pausing the login stream. <ul style="list-style-type: none"> • 1: The server supports optimized pause and resume. • 0: The server does not support optimized pause and resume. If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_OPT_PAUSE should be specified. If absent, a default value of 0 is assumed.
supportOMMPost	Optional. Indicates whether the provider supports OMM Posting: <ul style="list-style-type: none"> • 1: The provider supports OMM Posting and the user is permissioned. • 0: The provider supports the OMM Post feature, but the user is not permissioned. • If this element is not present, then the server does not support OMM Post feature. If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_POST should be specified. If absent, a default value of 0 is assumed.

Table 105: LoginSupportFeatures Members

MEMBER	DESCRIPTION
supportProviderDictionaryDownload	<p>Optional. Indicates whether the non-interactive provider can request dictionaries from the Refinitiv Real-Time Advanced Data Hub:</p> <ul style="list-style-type: none"> • 1: The non-interactive provider can request dictionaries from the Refinitiv Real-Time Advanced Data Hub. • 0: The non-interactive provider cannot request dictionaries from the Refinitiv Real-Time Advanced Data Hub. <p>If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_PROVIDER_DICTIONARY_DOWNLOAD should be specified. If absent, a default value of 0 is assumed.</p>
supportStandby	<p>Optional. Indicates whether the provider supports warm standby functionality. If supported, a provider can run as an active or a standby server, where the active will behave as usual. The standby will respond to item requests only with the message header and will forward any state changing information. When informed of an active's failure, the standby begins sending responses and takes over as active.</p> <ul style="list-style-type: none"> • 1: The provider supports a role of active or standby in a warm standby group. • 0: The provider does not support warm standby functionality. <p>If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_STANDBY should be specified. If absent, a default value of 0 is assumed.</p>
supportViewRequests	<p>Optional. Indicates whether the provider supports dynamic view functionality, which allows a user to request specific response information.</p> <ul style="list-style-type: none"> • 1: The provider supports dynamic view functionality. • 0: The provider does not support dynamic view functionality. <p>If present, a flags value of LoginSupportFeaturesFlags.HAS_SUPPORT_VIEW should be specified. If absent, a default value of 0 is assumed.</p>

Table 105: LoginSupportFeatures Members

8.3.2.4 Login Support Feature Set Flag Enumeration Values

For detailed information on batch functionality, posting, 'pause and resume,' and views, refer to the *Transport API Java Edition Developers Guide*.

FLAG ENUMERATION	MEANING
LoginSupportFeaturesFlags.HAS_SUPPORT_BATCH_CLOSES	Indicates the presence of supportBatchCloses . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_BATCH_REISSUES	Indicates the presence of supportBatchReissues . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_BATCH_REQUESTS	Indicates the presence of supportBatchRequests . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_ENH_SL	Indicates the presence of supportEnhancedSymbolList . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_OPT_PAUSE	Indicates the presence of supportOptimizedPauseResume . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_POST	Indicates the presence of supportOMMPost . If absent, a value of 0 is assumed.

Table 106: LoginSupportFeaturesFlags

FLAG ENUMERATION	MEANING
LoginSupportFeaturesFlags.HAS_SUPPORT_PROVIDER_DICTIONARY_DOWNLOAD	Indicates the presence of supportProviderDictionaryDownload . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_STANDBY	Indicates the presence of supportStandby . If absent, a value of 0 is assumed.
LoginSupportFeaturesFlags.HAS_SUPPORT_VIEW	Indicates the presence of supportViewRequests . If absent, a value of 0 is assumed.

Table 106: LoginSupportFeaturesFlags (Continued)**8.3.2.5 Login Connection Config Members**

MEMBER	DESCRIPTION
numStandbyServers	Required . Indicates the number of servers in the serverList that the consumer can use as standby servers when using warm standby.
serverList	Required . A list of servers to which the consumer may connect when using warm standby.

Table 107: LoginConnectionConfig Members**8.3.2.6 Login Connection Config Methods**

METHOD NAME	DESCRIPTION
clear	Clears a LoginConnectionConfig object for reuse.
copy	Performs a deep copy of a LoginConnectionConfig object.

Table 108: LoginConnectionConfig Methods**8.3.2.7 Server Info Members**

MEMBER	DESCRIPTION
flags	Required . Indicates the presence of optional server information members. For details, refer to Section 8.3.2.8.
hostname	Required . Indicates the server's hostname .
loadFactor	Optional . Indicates the load information for this server. If present, a flags value of ServerInfoFlags.HAS_LOAD_FACTOR should be specified.
port	Required . Indicates the server's port number for connections.
ServerIndex	Required . Provides the index value to this server.
ServerType	Optional . Indicates whether this server is an active or standby server. If present, a flags value of ServerInfoFlags.HAS_TYPE should be specified, populated by Login.ServerTypes .

Table 109: ServerInfo Members

8.3.2.8 Server Info Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServerInfoFlags.HAS_LOAD_FACTOR	Indicates presence of loadFactor information.
ServerInfoFlags.HAS_TYPE	Indicates presence of ServerType .

Table 110: ServerInfo Flags

8.3.2.9 Server Info Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServerInfo object. Useful for object reuse.
copy	Performs a deep copy of a ServerInfo object.

Table 111: ServerInfo Methods

8.3.3 Login Status

OMM provider and non-interactive provider applications use the **Login Status** message to convey state information associated with the login stream. Such state information can indicate that a login stream cannot be established or to inform a consumer of a state change associated with an open login stream.

The login status message can also reject a login request or close an existing login stream. When a status message closes a login stream, any other open streams associated with the user are also closed.

The **LoginStatus** represents all members of a login status message and allows for simplified use in OMM applications that leverage RDMs. This structure follows the behavior and layout defined in the Enterprise Transport API Java Edition *Refinitiv Domain Models Usage Guide*.

8.3.3.1 Login Status Members

MEMBER	DESCRIPTION
authenticationErrorCode	<p>Optional. If present, a flags value of LoginStatusFlags.HAS_AUTHN_ERROR_CODE should be specified.</p> <p>authenticationErrorCode is specific to deployments using Refinitiv Real-Time Distribution System Authentication, and specifies an error code. A code of 0 indicates no error condition. For further information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i>.^a</p>
authenticationErrorText	<p>Optional. If present, a flags value of LoginStatusFlags.HAS_AUTHN_ERROR_TEXT should be specified.</p> <p>Specifies any text associated with the specified authenticationErrorCode. For further information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i>.^a</p>
flags	Required. Indicates the presence of optional login status members. For details, refer to Section 8.3.3.2.
rdmMsgBase	Required. Specifies the login message type (i.e., LoginMsgType.STATUS for login status).
stateState	<p>Optional. If present, a flags value of LoginStatusFlags.HAS_STATE should be specified.</p> <p>Indicates the state of the login stream. When rejecting a login the state should be:</p> <ul style="list-style-type: none"> • streamState = StreamStates.CLOSED or StreamStates.CLOSED_RECOVER • dataState = DataStates.SUSPECT • StateCode = StateCodes.NOT_ENTITLED <p>For more information on State, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>

Table 112: **LoginStatus** Members

MEMBER	DESCRIPTION
userNameType	<p>Optional. If present, a flags value of <code>LoginStatusFlags.HAS_USERNAME_TYPE</code> should be specified. If absent, a default value of <code>Login.UserIdTypes.NAME</code> is assumed.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • <code>Login.UserIdTypes.NAME = 1</code> • <code>Login.UserIdTypes.EMAIL_ADDRESS = 2</code> • <code>Login.UserIdTypes.TOKEN = 3</code> • <code>Login.UserIdTypes.COOKIE = 4</code> • <code>Login.UserIdTypes.AUTHN_TOKEN = 5</code> <p>A type of <code>Login.UserIdTypes.NAME</code> typically corresponds to a Data Access Control System user name and can be used to authenticate and permission a user.</p> <p><code>Login.UserIdTypes.TOKEN</code> is specified when using the AAA ('triple A') API. The user token is retrieved from the Authentication Manager application. To validate users, a provider application passes this user token to the AAA Gateway. This type of token periodically changes: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to documentation specific to the AAA API.</p> <p><code>Login.UserIdTypes.AUTHN_TOKEN</code> is specified when using Refinitiv Real-Time Distribution System Authentication. The authentication token should be specified in the <code>userName</code> member. This type of token can periodically change: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to the <i>Refinitiv Real-Time Distribution System Authentication User Manual</i>.^a</p>
userName	<p>Optional. If present, a flags value of <code>LoginStatusFlags.HAS_USERNAME</code> should be specified.</p> <p>When populated, this should match the <code>userName</code> in the login request.</p>

Table 112: LoginStatus Members (Continued)

a. For further details on Refinitiv Real-Time Distribution System Authentication, refer to the *Refinitiv Real-Time Distribution System Authentication User Manual*, accessible on [MyRefinitiv](#) in the Data Access Control System product documentation set.

8.3.3.2 Login Status Flag Enumeration Values

FLAG ENUMERATION	MEANING
<code>LoginStatusFlags.CLEAR_CACHE</code>	Indicates whether the receiver of the login status should clear any associated cache information.
<code>LoginStatusFlags.HAS_AUTHN_ERROR_CODE</code>	Indicates the presence of <code>authenticationErrorCode</code> .
<code>LoginStatusFlags.HAS_AUTHN_ERROR_TEXT</code>	Indicates the presence of <code>authenticationErrorText</code> .
<code>LoginStatusFlags.HAS_STATE</code>	<p>Indicates the presence of <code>State</code>.</p> <p>If absent, any previously conveyed state continues to apply.</p>
<code>LoginStatusFlags.HAS_USERNAME</code>	Indicates the presence of <code>userName</code> .
<code>LoginStatusFlags.HAS_USERNAME_TYPE</code>	<p>Indicates the presence of <code>userNameType</code>.</p> <p>If absent a <code>userNameType</code> of <code>Login.UserIdTypes.NAME</code> is assumed.</p>

Table 113: LoginStatus Flags

8.3.4 Login Close

A **Login Close** message is encoded and sent by OMM consumer applications. This message allows a consumer to log out of the system. Closing a login stream is equivalent to a **Close All** type of message, where all open streams are closed (i.e., all streams associated with the user). A provider can log off a user and close all of that user's streams via a login status message, see Section 8.3.3.

MEMBER	DESCRIPTION
rdmMsgType	Required. Specifies the login message type (for a login close, this will be <code>LoginMsgType.CLOSE</code>).

Table 114: `LoginClose` Member

8.3.5 Login Consumer Connection Status

The **Login Consumer Connection Status** informs an interactive provider of its role in a **Warm Standby** group, either as an **Active** or **Standby** provider. An active provider behaves normally; however a standby provider responds to requests only with a message header (allowing a consumer application to confirm the availability of requested data across active and standby servers), and forwards any state-related messages (i.e., unsolicited refresh messages, status messages). A standby provider aggregates changes to item streams whenever possible. If a provider changes from Standby to Active via this message, all aggregated update messages are passed along. If aggregation is not possible, a full, unsolicited refresh message is passed along.

The consumer application is responsible for ensuring that items are available and equivalent across all providers in a warm standby group. This includes managing state and availability differences as well as item group differences.

The `LoginConsumerConnectionStatus` relies on the `GenericMsg` and represents all members necessary for applications that leverage RDMs. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.3.5.1 Login Consumer Connection Status Members

MEMBER	DESCRIPTION
flags	Required. Indicate the presence of optional login consumer connection status members. For details, refer to Section 8.3.5.2.
rdmMsgBase	Required. Indicates the Login Message type (for login connection status, set to <code>LoginMsgType.CONSUMER_CONNECTION_STATUS</code>).
warmStandbyInfo	Optional. Includes <code>LoginWarmStandbyInfo</code> to convey the state of the upstream provider. For details, refer to Section 8.3.5.3. If present, a flags value of <code>LoginConsumerConnectionStatusFlags.HAS_WARM_STANDBY_INFO</code> should be specified.

Table 115: `LoginConsumerConnectionStatus` Members

8.3.5.2 Login Consumer Connection Status Flag Enumeration Value

FLAG ENUMERATION	DESCRIPTION
<code>LoginConsumerConnectionStatusFlags.HAS_WARM_STANDBY_INFO</code>	Indicates presence of <code>warmStandbyInfo</code> .

Table 116: `LoginConsumerConnectionStatus` Flags

8.3.5.3 Login Warm Standby Info Members

MEMBER	DESCRIPTION
action	Required. Indicates how a cache of Warm Standby content should apply this information. For information on MapEntry actions, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
warmStandbyMode	Required. Indicates whether a server is active (Login.ServerTypes.ACTIVE) or standby (Login.ServerTypes.SERVER).

Table 117: **LoginWarmStandbyInfo** Members

8.3.5.4 Login Warm Standby Info Methods

METHOD NAME	DESCRIPTION
clear	Clears a LoginWarmStandbyInfo for reuse.
copy	Performs a deep copy of a LoginWarmStandbyInfo .

Table 118: **LoginWarmStandbyInfo** Methods

8.3.6 Login Round Trip Time Message Use

Interactive Provider applications use Login Round Trip Time messages to measure the full roundtrip latency time between the provider and consumer. You enable Round Trip Time by setting the **LoginAttribFlags.HAS_CONSUMER_SUPPORT_RTT** flag on the initial Login RDM request message. When **LoginAttribFlags.HAS_CONSUMER_SUPPORT_RTT** is set on the consumer, the Reactor attempts to reflect the Round Trip Time message whenever the provider sends a Round Trip Time message, and the login callback will contain the incoming Round Trip Time message for informational purposes. The Consumer application does not need to take further action to handle Round Trip Time messages.

For more specific usage information about this message type, refer to the Enterprise Transport API Java Edition *RDM Usage Guide*.

8.3.6.1 Login Round Trip Time Members

MEMBER	DESCRIPTION
flags	Required. Indicates the presence of optional Round Trip Time members. For details, refer to Section 8.3.6.2.
rdmMsgBase	Required. Contains general message information, such as streamId and domainType .
rtLatency	Specifies the previous Round Trip Latency value (in microseconds) calculated by the provider.
tcpRetrans	Indicates the total number of TCP retransmissions.
ticks	Required. Specifies the tick count sent by the provider. After receiving ticks , the consumer must reflect this value back to the provider using this element.

Table 119: Login Round Trip Time Members

8.3.6.2 Login Round Trip Time Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
HAS_TCP_RETRANS	Indicates the presence of the <code>tcpRetrans</code> member.
PROVIDER_DRIVEN	Indicates that this interaction was driven by the provider, not an interactive consumer.
ROUND_TRIP_LATENCY	Indicates the presence of the <code>rtLatency</code> member.

Table 120: Login Round Trip Time Flag Enumeration Values

8.3.6.3 Login Round Trip Time Utility Methods

The Enterprise Transport API provides the following utility method for use with Login Round Trip Time Messages.

METHOD NAME	DESCRIPTION
clear	Clears a <code>LoginRTT</code> object for reuse.
copy	Performs a deep copy of a <code>LoginRTT</code> object.

Table 121: Login Round Trip Time Utility Methods

8.3.7 Login Post Message Use

OMM consumer applications can encode and send data for any item via Post messages on the item's login stream. This is known as **off-stream posting** because items are posted without using that item's dedicated stream. Posting an item on its own dedicated stream is referred to as **on-stream posting**.

When an application is off-stream posting, `MsgKey` information is required on the `PostMsg`. For more details on posting, refer to the Enterprise Transport API Java Edition *Developers Guide*.

8.3.8 Login Ack Message Use

OMM provider applications encode and send Ack messages to acknowledge the receipt of Post messages. An Ack message is used whenever a consumer posts and asks for acknowledgments. For more details on posting, see the Enterprise Transport API Java Edition *Developers Guide*.

8.3.9 Login Attributes

On a Login Request or Login Refresh message, the **LoginAttrib** can send additional authentication information and user preferences between components.

8.3.9.1 Login Attrib Members

The following table lists the elements available on a **LoginAttrib**.

MEMBER	DESCRIPTION
allowSuspectData	<p>Indicates how the consumer application wants to handle suspect data.</p> <ul style="list-style-type: none"> • 1: Indicates that the consumer application allows for suspect streamState information. If absent, a default value of 1 is assumed. • 0: Indicates that the consumer application wants suspect data to cause the stream to close with a StreamStates.CLOSED_RECOVER state. <p>If present, a flags value of LoginAttribFlags.HAS_ALLOW_SUSPECT_DATA should be specified.</p>
applicationId	<p>Indicates the application ID.</p> <ul style="list-style-type: none"> • If populated in a login request, applicationId should be set to the DACS applicationId. If the server authenticates with DACS, the consumer application may be required to pass in a valid application id. If initializing LoginRequest using initDefaultRequest, an applicationId of 256 will be used. • If populated in a login refresh, applicationId should match the applicationId used in the login request. <p>If present, a flags value of LoginAttribFlags.HAS_APPLICATION_ID should be specified.</p>
applicationName	<p>Indicates the application name.</p> <ul style="list-style-type: none"> • If populated in a login request, the applicationName identifies the OMM consumer or OMM non-interactive provider. If initializing LoginRequest using initDefaultRequest, the applicationName is set to upa. • If populated in a login refresh, the applicationName identifies the OMM provider. <p>If present, a flags value of LoginAttribFlags.HAS_APPLICATION_NAME should be specified.</p>
flags	<p>Required. Indicates the presence of optional login attribute members.</p> <p>For details, refer to Section 8.3.9.3.</p>
position	<p>Indicates the DACS position.</p> <ul style="list-style-type: none"> • When populated in a login request, position should match the position contained in the login request and the DACS position (if using DACS). If the server is authenticating with DACS, the consumer application might be required to pass in a valid position. If initializing LoginRequest using initDefaultRequest, the IP address of the system on which the application runs will be used. • When populated in a login refresh, this should match the position contained in the login request <p>If present, a flags value of LoginAttribFlags.HAS_POSITION should be specified.</p>

Table 122: **LoginAttrib** Members

MEMBER	DESCRIPTION
providePermissionExpressions	<p>Indicates whether the consumer wants permission expression information. Permission expressions allow for items to be proxy-permissioned by a consumer via content-based entitlements.</p> <ul style="list-style-type: none"> • 1: Requests that permission expression information be sent with responses. If absent, a default value of 1 is assumed. • 0: Indicates that the consumer does not want permission expression information. <p>If present, a flags value of LoginAttribFlags.HAS_PROVIDE_PERM_EXPR should be specified.</p>
providePermissionProfile	<p>Indicates whether the consumer desires the permission profile. An application can use the permission profile to perform proxy permissioning.</p> <p>If present, a flags value of LoginAttribFlags.HAS_PROVIDE_PERM_PROFILE should be specified.</p> <ul style="list-style-type: none"> • 1: Indicates that the consumer wants the permission profile. If absent, a default value of 1 is assumed. • 0: Indicates the consumer does not want the permission profile.
singleOpen	<p>Indicates which application the consumer wants to drive stream recovery.</p> <p>If present, a flags value of LoginAttribFlags.HAS_SINGLE_OPEN should be specified.</p> <ul style="list-style-type: none"> • 1: Indicates that the consumer application wants the provider to drive stream recovery. If absent, a default value of 1 is assumed. • 0: Indicates that the consumer application drives stream recovery.
supportProviderDictionaryDownload	<p>Indicates whether the interactive provider can request dictionaries from the Refinitiv Real-Time Advanced Data Hub:</p> <ul style="list-style-type: none"> • 1: The interactive provider can request dictionaries from the Refinitiv Real-Time Advanced Data Hub. • 0: The interactive provider cannot request dictionaries from the Refinitiv Real-Time Advanced Data Hub. <p>If present, a flags value of LoginAttribFlags.HAS_PROVIDER_SUPPORT_DICTIONARY_DOWNLOAD should be specified. If absent, a default value of 0 is assumed.</p>
supportRTTMonitoring	<p>Indicates whether the consumer supports the Round Trip Time monitoring feature in the login stream.</p> <p>If present, for both provider and consumer, a flags value of LoginAttribFlags.HAS_CONSUMER_SUPPORT_RTT should be specified. A value of 2 indicates support for the Round Trip Time monitoring feature.</p>

Table 122: LoginAttrib Members (Continued)

8.3.9.2 Login Attrib Methods

METHOD NAME	DESCRIPTION
clear	Clears a LoginAttrib object for reuse.
copy	Performs a deep copy of a LoginAttrib object.

Table 123: **LoginAttrib** Methods

8.3.9.3 Login Attrib Flag Enumeration Values

FLAG ENUMERATION	MEANING
HAS_ALLOW_SUSPECT_DATA	Indicates the presence of allowSuspectData . If absent, a value of 1 is assumed.
HAS_APPLICATION_ID	Indicates the presence of applicationId .
HAS_APPLICATION_NAME	Indicates the presence of applicationName .
HAS_POSITION	Indicates the presence of position .
HAS_PROVIDE_PERM_EXPR	Indicates the presence of providePermissionExpressions . If absent, a value of 1 is assumed.
HAS_PROVIDE_PERM_PROFILE	Indicates the presence of providePermissionProfile . If absent, a value of 1 is assumed.
HAS_PROVIDER_SUPPORT_DICTIONARY_DOWNLOAD	Indicates the presence of supportProviderDictionaryDownload .
HAS_SINGLE_OPEN	Indicates the presence of singleOpen . If absent, a value of 1 is assumed.

Table 124: **LoginAttribFlags**

8.3.10 Login Message

LoginMsg is the base interface for all Login messages. It is provided for use with general login-specific functionality. The following table summarizes different login messages.

INTERFACE	DESCRIPTION
LoginClose	RDM Login Close.
LoginConsumerConnectionStatus	RDM Login Consumer Connection Status.
LoginRefresh	RDM Login Refresh
LoginRequest	RDM Login Request.
LoginStatus	RDM Login Status.
LoginRTT	RDM Login Round Trip Time

Table 125: **LoginMsg** Interfaces

8.3.11 Login Message Utility Method

FUNCTION NAME	DESCRIPTION
copy	Performs a deep copy of a LoginMsg object.

Table 126: LoginMsg Utility Method

8.3.12 Login Encoding and Decoding

8.3.12.1 Login Encoding and Decoding Methods

METHOD NAME	DESCRIPTION
decode	<p>Decodes a Login message. The decoded message may refer to encoded data from the original message. If you want to store the message, use the appropriate copy method for the decoded message to create a full copy.</p> <p>Each login subinterface overrides this method to decode specific login message.</p>
encode	<p>Encodes a Login message. This method takes the EncodeIterator as a parameter into which the encoded content is populated.</p> <p>Each login subinterface overrides this method to encode specific login message.</p>

Table 127: Login Encoding and Decoding Methods

8.3.12.2 Encoding a Login Request

```

EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
LoginRequest loginRequest = (LoginRequest)LoginMsgFactory.createMsg();

/* Clear the Login Request object. */
loginRequest.clear();

/* Set login message type - required as object created by LoginMsgFactory.createMsg() is generic Login */
/* object. */
loginRequest.rdmMsgType(LoginMsgType.REQUEST);

/* Set stream id. */
loginRequest.streamId(streamId);

/* Set flags indicating presence of optional members. */
loginRequest.applyHasAttrib();

/* Set UserName. */
loginRequest.userName().data("username");

/* Set ApplicationName */
loginRequest.attrib().applyHasApplicationName();
loginRequest.attrib().applicationName().data("upa");

/* Set ApplicationId */
loginRequest.attrib().applyHasApplicationId();
loginRequest.attrib().applicationId().data("256");

/* Set Position */
loginRequest.attrib().applyHasPosition();
loginRequest.attrib().position().data("127.0.0.1/net");

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
encodeIter.clear();
ret = encodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Encode the message. */
ret = loginRequest.encode(encodeIter);

```

Code Example 19: Login Request Encoding Example

8.3.12.3 Decoding a Login Request

```

DecodeIterator decodeIter = CodecFactory.createDecodeIterator();
LoginRequest loginRequest = (LoginRequest)LoginMsgFactory.createMsg();
Msg msg = CodecFactory.createMsg();

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
decodeIter.clear();
ret = decodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Decode the message to a Msg object. */
ret = msg.decode(decodeIter);

if (ret == CodecReturnCodes.SUCCESS && msg.domainType() == DomainTypes.LOGIN && msg.msgClass() ==
    MsgClasses.REQUEST)
{
    loginRequest.clear();
    loginRequest.rdmMsgType(LoginMsgType.REQUEST);

    ret = loginRequest.decode(decodeIter, msg);

    if(ret == CodecReturnCodes.SUCCESS)
    {
        /* Print username. */
        printf("Username: " + loginRequest.userName());

        if (loginRequest.checkHasAttrib())
        {
            LoginAttrib attrib = loginRequest.attrib();

            /* Print ApplicationName if present. */
            if(attrib.checkHasApplicationName())
                System.out.println("ApplicationName: " + attrib.applicationName().toString());

            /* Print ApplicationId if present. */
            if(attrib.checkHasApplicationId())
                System.out.println("ApplicationId: " + attrib.applicationId().toString());

            /* Print Position if present. */
            if(attrib.checkHasPosition())
                System.out.println("Position: " + attrib.position().toString());
        }
    }
}

```

Code Example 20: Login Request Decoding Example

8.3.12.4 Encoding a Login Refresh

```

EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
LoginRefresh loginRefresh = (LoginRefresh)LoginMsgFactory.createMsg();

/* Clear the Login Refresh object. */
loginRefresh.clear();

/* Set login message type - required as object created by LoginMsgFactory.createMsg() is generic Login */
/* object.*/
encodeIter.rdmMsgType(LoginMsgType.REFRESH);

/* Set stream id. */
loginRefresh.streamId(streamId);

/* Set flags indicating presence of optional members. */
loginRefresh.applyHasAttrib();
loginRefresh.applyHasUserName();

/* Set UserName. */
loginRefresh.userName().data("username");

/* Set ApplicationName */
loginRefresh.attrib().applyHasApplicationName();
loginRefresh.attrib().applicationName().data("upa");

/* Set ApplicationId */
loginRefresh.attrib().applyHasApplicationId();
loginRefresh.attrib().applicationId().data("256");

/* Set Position */
loginRefresh.attrib().applyHasPosition();
loginRefresh.attrib().position().data("127.0.0.1/net");

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
encodeIter.clear();
ret = encodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Encode the message. */
ret = loginRefresh.encode(encodeIter);

```

Code Example 21: Login Refresh Encoding Example

8.3.12.5 Decoding a Login Refresh

```

DecodeIterator decodeIter = CodecFactory.createDecodeIterator();
LoginRefresh loginRefresh = (LoginRefresh)LoginMsgFactory.createMsg();
Msg msg = CodecFactory.createMsg();

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
decodeIter.clear();
ret = decodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Decode the message to a Msg object. */
ret = msg.decode(decodeIter);

if (ret == CodecReturnCodes.SUCCESS && msg.domainType() == DomainTypes.LOGIN && msg.msgClass() ==
    MsgClasses.REFRESH)
{
    loginRefresh.clear();
    loginRefresh.rdmMsgType(LoginMsgType.REFRESH);

    ret = loginRefresh.decode(decodeIter, msg);

    if(ret == CodecReturnCodes.SUCCESS)
    {
        /* Print username. */
        if(loginRefresh.checkHasUserName())
            printf("Username: " + loginRefresh.userName().toString());

        if (loginRefresh.checkHasAttrib())
        {
            LoginAttrib attrib = loginRefresh.attrib();

            /* Print ApplicationName if present. */
            if(attrib.checkHasApplicationName())
                System.out.println("ApplicationName: " + attrib.applicationName().toString());

            /* Print ApplicationId if present. */
            if(attrib.checkHasApplicationId())
                System.out.println("ApplicationId: " + attrib.applicationId().toString());

            /* Print Position if present. */
            if(attrib.checkHasPosition())
                System.out.println("Position: " + attrib.position().toString());
        }
    }
}

```

Code Example 22: Login Refresh Decoding Example

8.4 RDM Source Directory Domain

The Source Directory domain model conveys information about:

- All available services and their capabilities, their supported domain types, services' states, quality of service, and item group information (associated with any particular service). Each service is associated with a unique **ServiceId**.
- Item group status, allowing a single message to change the state of all associated items. Thus, using the Source Directory domain an application can send a mass update for multiple items instead of sending a status message for each individual item. The consumer is responsible for applying any changes to its open items. For details, refer to Section 8.4.10.
- Source Mirroring between a Refinitiv Real-Time Advanced Data Hub and OMM interactive provider applications. The Source Directory exchanges this information via a specifically-formatted generic message as described in Section 8.4.6.

8.4.1 Directory Request

An OMM consumer application encodes and sends **Directory Request** messages to request information from an OMM provider about available services. A consumer may request information about all services by omitting the **serviceId** member, or request information about a specific service by setting it to the ID of the desired service.

The **DirectoryRequest** represents all members of a directory request message and is easily used in OMM applications that leverage RDMS. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.1.1 Directory Request Members

MEMBER	DESCRIPTION
filter	<p>Required. Indicates the service information in which the consumer is interested. The available flags are:</p> <ul style="list-style-type: none"> • <code>Directory.ServiceFilterFlags.INFO = 0x01</code> • <code>Directory.ServiceFilterFlags.STATE = 0x02</code> • <code>Directory.ServiceFilterFlags.GROUP = 0x04</code> • <code>Directory.ServiceFilterFlags.LOAD = 0x08</code> • <code>Directory.ServiceFilterFlags.DATA = 0x10</code> • <code>Directory.ServiceFilterFlagsLINK = 0x20</code> <p>In most cases, you should set the <code>Directory.ServiceFilterFlags.INFO</code>, <code>Directory.ServiceFilterFlags.STATE</code>, and <code>Directory.ServiceFilterFlags.GROUP</code>.</p>
flags	Required. Indicates the presence of optional directory request members. For details, refer to Section 8.4.1.2.
rdmMsgBase	Required. Specifies the directory message type (a directory request would be <code>DirectoryMsgType.REQUEST</code>).
ServiceId	<p>Optional.</p> <ul style="list-style-type: none"> • If not present, this indicates the consumer wants information about all available services. • If present, this indicates the ID of the service about which the consumer wants information. Additionally, a flags value of <code>DirectoryRequestFlags.HAS_SERVICE_ID</code> should be specified.

Table 128: DirectoryRequest Members

8.4.1.2 Directory Request Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
DirectoryRequestFlags.HAS_SERVICE_ID	Indicates the presence of ServiceId .
DirectoryRequestFlags.STREAMING	Indicates that the consumer wants to receive updates about directory information after the initial refresh.

Table 129: DirectoryRequest Flags

8.4.1.3 Directory Request Methods

METHOD NAME	DESCRIPTION
clear	Clears a DirectoryRequest object. Useful for object reuse.
copy	Performs a deep copy of a DirectoryRequest object.

Table 130: DirectoryRequest Utility Methods

8.4.2 Directory Refresh

A **Directory Refresh** message is encoded and sent by OMM provider and non-interactive provider applications. This message can provide information about the services supported by the provider application.

The **DirectoryRefresh** represents all members of a directory refresh message and is easily used in OMM applications that leverage RDMs. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.2.1 Directory Refresh Members

MEMBER	DESCRIPTION
filter	Required. Indicates the information being provided about supported services. This should match the filter of the consumer's DirectoryRequest . The available flags are: <ul style="list-style-type: none"> • <code>Directory.ServiceFilterFlags.INFO = 0x01</code> • <code>Directory.ServiceFilterFlags.STATE = 0x02</code> • <code>Directory.ServiceFilterFlags.GROUP = 0x04</code> • <code>Directory.ServiceFilterFlags.LOAD = 0x08</code> • <code>Directory.ServiceFilterFlags.DATA = 0x10</code> • <code>Directory.ServiceFilterFlagsLINK = 0x20</code>
flags	Required. Indicates the presence of optional directory refresh members. Refer to Section 8.4.2.2.
rdmMsgBase	Required. Specifies the type of directory message. For a directory refresh, send DirectoryMsgType.REFRESH .
sequenceNumber	Optional. If present, a flags value of DirectoryRefreshFlags.HAS_SEQ_NUM should be specified. sequenceNumber is a user-specified, item-level sequence number that the application can use to sequence messages in the stream.
ServiceId	Optional. If present, a flags value of DirectoryRefreshFlags.HAS_SERVICE_ID should be specified, which should match the ServiceId of the consumer's DirectoryRequest .
ServiceList	Optional. Contains a list of information about available services.
State	Required. Indicates stream and data state information. For further details on State , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 131: DirectoryRefresh Members

8.4.2.2 Directory Refresh Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
<code>DirectoryRefreshFlags.CLEAR_CACHE</code>	Indicates that any stored payload information associated with the directory stream should be cleared. This might happen if some portion of data is known to be invalid.
<code>DirectoryRefreshFlags.HAS_SEQ_NUM</code>	Indicates the presence of sequenceNumber .
<code>DirectoryRefreshFlags.HAS_SERVICE_ID</code>	Indicates the presence of ServiceId .
<code>DirectoryRefreshFlags.SOLICITED</code>	If present, this flag indicates that the directory refresh is solicited (i.e., it is in response to a request). The absence of this flag indicates that the refresh is unsolicited.

Table 132: DirectoryRefresh Flags

8.4.3 Directory Update

A **Directory Update** message is encoded and sent by OMM provider and non-interactive provider applications. This message can provide information about new or removed services, or changes to existing services.

The **DirectoryUpdate** represents all members of a directory update message and allows for simplified use in OMM applications that leverage RDMS. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.3.1 Directory Update Members

MEMBER	DESCRIPTION
filter	<p>Optional. Indicates what information is provided about supported services. This should match the filter of the consumer's DirectoryRequest.</p> <p>If present, a flags value of DirectoryUpdateFlags.HAS_FILTER should be specified.</p> <p>Available flags are:</p> <ul style="list-style-type: none"> • Directory.ServiceFilterFlags.INFO = 0x01 • Directory.ServiceFilterFlags.STATE = 0x02 • Directory.ServiceFilterFlags.GROUP = 0x04 • Directory.ServiceFilterFlags.LOAD = 0x08 • Directory.ServiceFilterFlags.DATA = 0x10 • Directory.ServiceFilterFlags.LINK = 0x20
flags	<p>Required. Indicates the presence of optional directory update members. For details refer to Section 8.4.3.2.</p>
sequenceNumber	<p>Optional. A user-specified, item-level sequence number which the application can use to sequence messages in this stream.</p> <p>If present, a flags value of DirectoryUpdateFlags.HAS_SEQ_NUM should be specified.</p>
ServiceId	<p>Optional. This member's value must match the ServiceId of the consumer's DirectoryRequest.</p> <p>If present, a flags value of DirectoryUpdateFlags.HAS_SERVICE_ID should be specified.</p>
ServiceList	<p>Optional. Contains a list of information about available services.</p>
rdmMsgBase	<p>Required. Specifies the message type. For a directory update, send DirectoryMsgType.UPDATE.</p>

Table 133: DirectoryUpdate Members

8.4.3.2 Directory Update Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
DirectoryUpdateFlags.HAS_FILTER	Indicates the presence of filter .
DirectoryUpdateFlags.HAS_SEQ_NUM	Indicates the presence of sequenceNumber .
DirectoryUpdateFlags.HAS_SERVICE_ID	Indicates the presence of ServiceId .

Table 134: DirectoryUpdate Flags

8.4.4 Directory Status

OMM providers and non-interactive providers use the **Directory Status** message to convey state information associated with the directory stream. Such state information can indicate that a directory stream cannot be established or to inform a consumer of a state change associated with an open directory stream. An application can also use the Directory Status message to close an existing directory stream.

The **DirectoryStatus** represents all members of a directory status message and allows for simplified use in OMM applications that leverage RDMS. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.4.1 Directory Status Members

MEMBER	DESCRIPTION
filter	<p>Optional. If present, a flags value of DirectoryStatusFlags.HAS_FILTER should be specified. Indicates what information is being provided about supported services. This should match the filter of the consumer's DirectoryRequest. The available flags are:</p> <ul style="list-style-type: none"> • Directory.ServiceFilterFlags.INFO = 0x01 • Directory.ServiceFilterFlags.STATE = 0x02 • Directory.ServiceFilterFlags.GROUP = 0x04 • Directory.ServiceFilterFlags.LOAD = 0x08 • Directory.ServiceFilterFlags.DATA = 0x10 • Directory.ServiceFilterFlagsLINK = 0x20
flags	<p>Required. Indicates the presence of optional directory status members. For details, refer to Section 8.4.4.2.</p>
ServiceId	<p>Optional. If present, a flags value of DirectoryStatusFlags.HAS_SERVICE_ID should be specified. This member should match the ServiceId of the consumer's DirectoryRequest.</p>
State	<p>Optional. Indicates the state of the directory stream. If present, a flags value of DirectoryStatusFlags.HAS_STATE should be specified. For more information on State, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i>.</p>
rdmMsgBase	<p>Required. Specifies the message type. For a directory status, send DirectoryMsgType.STATUS.</p>

Table 135: DirectoryStatus Members

8.4.4.2 Directory Status Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
DirectoryStatusFlags.CLEAR_CACHE	Indicates that any stored payload data associated with the directory stream should be cleared. This might happen if some portion of data is known to be invalid.
DirectoryStatusFlags.HAS_FILTER	Indicates the presence of filter .
DirectoryStatusFlags.HAS_SERVICE_ID	Indicates the presence of ServiceId .
DirectoryStatusFlags.HAS_STATE	Indicates the presence of State . If not present, any previously conveyed state should continue to apply.

Table 136: DirectoryStatus Flags

8.4.4.3 Directory Status Methods

METHOD NAME	DESCRIPTION
clear	Clears a DirectoryStatus . Useful for reuse.
copy	Performs a deep copy of a DirectoryStatus .

Table 137: **DirectoryStatus** Utility Methods

8.4.5 Directory Close

A **Directory Close** message is encoded and sent by OMM consumer applications. This message allows a consumer to close an open directory stream. A provider can close the directory stream via a Directory Status message; for details refer to Section 8.4.4.

MEMBER	DESCRIPTION
rdmMsgBase	Required. Specifies the directory message type. For a Directory Close message, set rdmMsgBase to DirectoryMsgType.CLOSE .

Table 138: **DirectoryClose** Member

8.4.6 Directory Consumer Status

The **Directory Consumer Status** is sent by OMM consumer applications to inform a service of how the consumer is used for **Source Mirroring**. This message is primarily informational.

The **DirectoryConsumerStatus** relies on the **GenericMsg** and represents all members necessary for applications that leverage RDMS. This structure follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.6.1 Directory Consumer Status Members

MEMBER	DESCRIPTION
consumerServiceStatusList	Optional. Contains a list of ConsumerStatusService object.
rdmMsgBase	Required . Specifies the directory message type. For a directory consumer status, set rdmMsgBase to DirectoryMsgType.CONSUMER_STATUS .

Table 139: **DirectoryConsumerStatus** Members

8.4.6.2 Directory Consumer Status Service Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of Source Mirroring content should apply this information. For information on MapEntry actions, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
ServiceId	Required . Indicates the service associated with this status.
sourceMirroringMode	Required . Indicates how the consumer is using the service. Available enumerations are: <ul style="list-style-type: none"> • Directory.SourceMirroringMode.ACTIVE_NO_STANDBY = 0, • Directory.SourceMirroringMode.ACTIVE_WITH_STANDBY = 1, • Directory.SourceMirroringMode.STANDBY = 2

Table 140: **ConsumerStatusService** Members

8.4.7 Directory Service

A **Service** object conveys information about a service. A list of **Services** forms the **serviceServiceList** member of the **DirectoryRefresh** and **DirectoryUpdate** messages.

The members of a **Service** represent the different filters used to categorize service information.

8.4.7.1 Service Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of the service should apply this information. For information on MapEntry actions, refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
data	Optional . Contains data that applies to the items requested from the service and represents the Source Directory Data Filter. If present, a flags value of ServiceFlags.HAS_DATA should be specified.
flags	Required . Indicates the presence of optional service members. For details, refer to Section 8.4.7.2.
groupStateList	Optional . Contains a list of elements indicating changes to item groups and represents the Source Directory Group filter.
info	Optional . Contains information related to the Source Directory Info Filter. If present, a flags value of ServiceFlags.HAS_INFO should be specified.
link	Optional . Contains information about upstream sources that provide data to this service and represents the Source Directory Link Filter. If present, a flags value of ServiceFlags.HAS_LINK should be specified.
load	Optional . Contains information about the service's operating workload and represents the Source Directory Load Filter. If present, a flags value of ServiceFlags.HAS_LOAD should be specified.
ServiceId	Required . Indicates the service associated with this Service .
State	Optional . Contains information related to the Source Directory State Filter. If present, a flags value of ServiceFlags.HAS_STATE should be specified.

Table 141: Service Members

8.4.7.2 Service Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceFlags.HAS_DATA	Indicates the presence of data .
ServiceFlags.HAS_INFO	Indicates the presence of info .
ServiceFlags.HAS_LINK	Indicates the presence of link .
ServiceFlags.HAS_LOAD	Indicates the presence of load .
ServiceFlags.HAS_STATE	Indicates the presence of state .

Table 142: Service Flags

8.4.7.3 Service Methods

METHOD NAME	DESCRIPTION
clear	Clears a Service object. Useful for object reuse.
copy	Performs a deep copy of a Service object.

Table 143: Service Utility Methods

8.4.8 Directory Service Info Filter

A **ServiceInfo** object conveys information that identifies the service and the content it provides. The **ServiceInfo** object represents the Source Directory Info filter. More information about the Info filter is available in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.8.1 Service Info Members

MEMBER	DESCRIPTION
acceptingConsumerStatus	Optional. Indicates whether this service supports accepting DirectoryConsumerStatus messages for Source Mirroring. Available values are: <ul style="list-style-type: none"> • 1: The service will accept Consumer Status messages. If not present, a value of 1 is assumed. • 0: The service will not accept Consumer Status messages. If present, a flags value of ServiceInfoFlags.HAS_ACCEPTING_CONS_STATUS should be specified.
action	Required. Indicates how a service info cache should apply this information. For information on FilterEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
capabilitiesList	Required. Contains a list of capabilities that the service supports. Populated by domain types.
dictionariesProvidedList	Optional. Contains a list of elements that identify dictionaries that can be requested from this service. If present, a flags value of ServiceInfoFlags.HAS_DICTS_PROVIDED should be specified.
dictionariesUsedList	Optional. Contains a list of elements that identify dictionaries used to decode data from this service. If present, a flags value of ServiceInfoFlags.HAS_DICTS_USED should be specified.
flags	Required. Indicates the presence of optional service info members. For details, refer to Section 8.4.8.2.
isSource	Optional. Indicates whether the service is provided directly by a source or represents a group of sources. <ul style="list-style-type: none"> • 1: The service is provided directly by a source • 0: The service represents a group of sources. If absent, a value of 0 is assumed. If present, a flags value of ServiceInfoFlags.HAS_IS_SOURCE should be specified.
itemList	Optional. Specifies a name that can be requested on the DomainTypes.SYMBOL_LIST domain to get a list of all items available from this service. If present, a flags value of ServiceInfoFlags.HAS_ITEM_LIST should be specified.

Table 144: ServiceInfo Members

MEMBER	DESCRIPTION
QosList	Optional. Contains a list of elements that identify the available Qualities of Service. If present, a flags value of ServiceInfoFlags.HAS_QOS should be specified.
ServiceName	Required. Indicates the name of the service.
supportsOutOfBandSnapshots	Optional. Indicates whether this service supports making snapshot requests even when the OpenLimit is reached. Available values are: <ul style="list-style-type: none"> • 1: Snapshot requests are allowed. If not present, a value of 1 is assumed. • 0: Snapshot requests are not allowed. If present, a flags value of ServiceInfoFlags.HAS_SUPPORT_OOB_SNAPSHOTS should be specified.
supportsQosRange	Optional. Indicates whether this service supports specifying a range of Qualities of Service when requesting an item. For further information, refer to the Qos and worstQos members of the RequestMsg in the Enterprise Transport API Java Edition <i>Developers Guide</i> . Available values are: <ul style="list-style-type: none"> • 1: Quality of Service Range requests are supported. • 0: Quality of Service Range requests are not supported. If not present, a value of 0 is assumed. If present, a flags value of ServiceInfoFlags.HAS_SUPPORT_QOS_RANGE should be specified.
vendor	Optional. Identifies the vendor of the data. If present, a flags value of ServiceInfoFlags.HAS_VENDOR should be specified.

Table 144: ServiceInfo Members (Continued)

8.4.8.2 Service Info Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceInfoFlags.HAS_ACCEPTING_CONS_STATUS	Indicates the presence of acceptingConsumerStatus .
ServiceInfoFlags.HAS_DICTS_PROVIDED	Indicates the presence of dictionariesProvidedList .
ServiceInfoFlags.HAS_DICTS_USED	Indicates the presence of dictionariesUsedList .
ServiceInfoFlags.HAS_IS_SOURCE	Indicates the presence of isSource .
ServiceInfoFlags.HAS_ITEM_LIST	Indicates the presence of itemList .
ServiceInfoFlags.HAS_QOS	Indicates the presence of QosList .
ServiceInfoFlags.HAS_SUPPORT_OOB_SNAPSHOTS	Indicates the presence of supportsOutOfBandSnapshots .
ServiceInfoFlags.HAS_SUPPORT_QOS_RANGE	Indicates the presence of supportsQosRange .
ServiceInfoFlags.HAS_VENDOR	Indicates the presence of vendor .

Table 145: ServiceInfo Flags

8.4.8.3 Service Info Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceInfo object. Useful for object reuse.
copy	Performs a deep copy of a ServiceInfo object.

Table 146: ServiceInfo Utility Methods

8.4.9 Directory Service State Filter

A **ServiceState** object conveys information about service's current state. It represents the Source Directory State filter. For more information about the State filter, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.9.1 Service State Members

MEMBER	DESCRIPTION
acceptingRequests	Indicates whether the immediate provider (to which the consumer is directly connected) can handle the request. Available values are: <ul style="list-style-type: none"> • 1: The service will accept new requests. • 0: The service does not currently accept new requests. If present, flags value of ServiceStateFlags.HAS_ACCEPTING_REQS should be specified.
action	Required . Indicates how a cache of the service state should apply this information. For details on FilterEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
flags	Required . Indicates the presence of optional service state members. For details refer to Section 8.4.9.2.
ServiceState	Required . Indicates whether the original provider of the data can respond to new requests. Requests can still be made if so indicated by acceptingRequests . Available values are: <ul style="list-style-type: none"> • 1: The original provider of the data is available. • 0: The original provider of the data is not currently available.
status	This status should be applied to all open items associated with this service. If present, flags value of ServiceStateFlags.HAS_STATUS should be specified.

Table 147: ServiceState Members

8.4.9.2 Service State Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceStateFlags.HAS_ACCEPTING_REQS	Indicates the presence of acceptingRequests .
ServiceStateFlags.HAS_STATUS	Indicates the presence of status .

Table 148: ServiceState Flags

8.4.9.3 Service State Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceState . Useful for reuse.
copy	Performs a deep copy of a ServiceState .

Table 149: ServiceState Utility Methods

8.4.10 Directory Service Group Filter

A **ServiceGroup** object is used to convey status and name changes for an item group. It represents the Source Directory Group filter. For further details about the Group filter, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.10.1 Service Group Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of the service group should apply this information. For further details on filterEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
flags	Required . Indicates the presence of optional service group members. For details, refer to Section 8.4.10.2.
group	Required . Identifies the name of the item group being changed.
mergedToGroup	Optional . Specifies the new group name. All items of the specified group are put into this new group. If present, a flags value of ServiceGroupFlags.HAS_MERGED_TO_GROUP should be specified.
status	Optional . Specifies the status to apply to all open items associated with the group specified by group . If present, a flags value of ServiceGroupFlags.HAS_STATUS should be specified.

Table 150: ServiceGroup Members

8.4.10.2 Service Group Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceGroupFlags.HAS_MERGED_TO_GROUP	Indicates the presence of mergedToGroup .
ServiceGroupFlags.HAS_STATUS	Indicates the presence of status .

Table 151: ServiceGroup Flags

8.4.10.3 Service Group Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceGroup . Useful for reuse.
copy	Performs a deep copy of a ServiceGroup .

Table 152: ServiceGroup Utility Methods

8.4.11 Directory Service Load Filter

A **ServiceLoad** object conveys the workload of a service. It represents the Source Directory Load filter. For further details on the Service Load filter, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.11.1 Service Load Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of the service load should apply this information. For information on FilterEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
flags	Required . Indicates presence of optional service load members. For details, refer to Section 8.4.11.2.
loadFactor	If present, flags value of ServiceLoadFlags.HAS_LOAD_FACTOR should be specified. Indicates the current workload on the source that provides data. A higher load factor indicates a higher workload. For more information, refer to the Enterprise Transport API Java Edition <i>Refinitiv Domain Model Usage Guide</i> .
openLimit	Specifies the maximum number of streaming requests that the service allows. If present, flags value of ServiceLoadFlags.HAS_OPEN_LIMIT should be specified.
openWindow	Specifies the maximum number of outstanding requests (i.e., requests awaiting a refresh) that the service allows. If present, flags value of ServiceLoadFlags.HAS_OPEN_WINDOW should be specified.

Table 153: ServiceLoad Members

8.4.11.2 Service Load Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceLoadFlags.HAS_LOAD_FACTOR	Indicates the presence of loadFactor .
ServiceLoadFlags.HAS_OPEN_LIMIT	Indicates the presence of openLimit .
ServiceLoadFlags.HAS_OPEN_WINDOW	Indicates the presence of openWindow .

Table 154: ServiceLoad Flags

8.4.11.3 Service Load Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceLoad . Useful for reuse.
copy	Performs a deep copy of a ServiceLoad .

Table 155: ServiceLoad Utility Methods

8.4.12 Directory Service Data Filter

A **ServiceData** object conveys the data to apply to all items of a service. It represents the Source Directory Data filter. For further details on the Data filter, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.12.1 Service Data Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of the service data should apply this information. For further details on FilterEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
data	Optional . Contains the encoded Buffer representing the data. The type of the data is given by dataType . If present, a flags value of ServiceDataFlags.HAS_DATA should be specified.
dataType	Optional . Specifies the DataType of the data. For information on DataTypes , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> . If present, a flags value of ServiceDataFlags.HAS_DATA should be specified.
flags	Required . Indicates the presence of optional service data members. For details, refer to Section 8.4.12.2.
type	Optional . Indicates the type of content present in data . Available enumerations are: <ul style="list-style-type: none">• Directory.DataTypes.TIME = 1• Directory.DataTypes.ALERT = 2• Directory.DataTypes.HEADLINE = 3• Directory.DataTypes.STATUS = 4 If present, flags value of ServiceDataFlags.HAS_DATA should be specified.

Table 156: ServiceData Members

8.4.12.2 Service Load Data Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceDataFlags.HAS_DATA	Indicates the presence of type , dataType , and data .

Table 157: ServiceData Flags

8.4.12.3 Service Data Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceData . Useful for reuse.
copy	Performs a deep copy of a ServiceData .

Table 158: ServiceData Methods

8.4.13 Directory Service Link Info Filter

A **ServiceLinkInfo** object conveys information about upstream sources that form a service. It represents the Source Directory Link filter. More information about the Service Link filter content is available in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

The **ServiceLinkInfo** object contains a list of **ServiceLink** objects that each represents an upstream source.

8.4.13.1 Service Link Info Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of the service link information should apply this information. For further information on FilterEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
linkList	Optional . Contains a list of ServiceLink object, each representing a source.

Table 159: ServiceLinkInfo Members

8.4.13.2 Service Link Info Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceLinkInfo . Useful for reuse.
copy	Performs a deep copy of a ServiceLinkInfo .

Table 160: ServiceLinkInfo Methods

8.4.14 Directory Service Link

A **ServiceLink** object conveys information about an upstream source. It represents an entry in the Source Directory Link filter and is used by the **linkList** member of the **ServiceLinkInfo** object. For further details on Service Link filter content, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.4.14.1 Service Link Members

MEMBER	DESCRIPTION
action	Required . Indicates how a cache of the service link should apply this information. For information on MapEntryActions , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
flags	Required . Indicates the presence of optional service link members. For details, refer to Section 8.4.14.2.
linkCode	Optional . Indicates additional information about the status of a source. Available enumerations are: <ul style="list-style-type: none"> • Directory.LinkCodes.NONE = 0 • Directory.LinkCodes.OK = 1 • Directory.LinkCodes.RECOVERY_STARTED = 2 • Directory.LinkCodes.RECOVERY_COMPLETED = 3 If present, a flags value of ServiceLinkFlags.HAS_CODE should be specified.
linkState	Required . Indicates whether the source is up or down. Available values are: <ul style="list-style-type: none"> • Directory.LinkStates.DOWN = 0 • Directory.LinkStates.UP = 1
name	Required . Specifies the name of the source. Sources with identical names are typically load-balanced sources.
text	Optional . Gives additional status details regarding the source. If present, a flags value of ServiceLinkFlags.HAS_TEXT should be specified.
type	Optional . Specifies whether the source is interactive or broadcast. Available enumerations are: <ul style="list-style-type: none"> • Directory.LinkTypes.INTERACTIVE = 1 • Directory.LinkTypes.BROADCAST = 2 If present, a flags value of ServiceLinkFlags.HAS_TYPE should be specified.

Table 161: ServiceLink Members

8.4.14.2 Service Link Enumeration Values

FLAG ENUMERATION	DESCRIPTION
ServiceLinkFlags.HAS_CODE	Indicates the presence of code .
ServiceLinkFlags.HAS_TEXT	Indicates the presence of text .
ServiceLinkFlags.HAS_TYPE	Indicates the presence of type .

Table 162: ServiceLink Flags

8.4.14.3 Service Link Methods

METHOD NAME	DESCRIPTION
clear	Clears a ServiceLink . Useful for reuse.
copy	Performs a deep copy of a ServiceLink .

Table 163: **ServiceLink** Methods

8.4.15 Directory Message

DirectoryMsg is the general purpose base interface for all directory messages. Different directory messages are summarized in the following table.

INTERFACE	DESCRIPTION
DirectoryClose	RDM Directory Close.
DirectoryConsumerConnectionStatus	RDM Directory Consumer Status.
DirectoryRefresh	RDM Directory Refresh.
DirectoryRequest	RDM Directory Request.
DirectoryStatus	RDM Directory Status.
DirectoryUpdate	RDM Directory Update.

Table 164: **DirectoryMsg** Interfaces

8.4.16 Directory Message Utility Methods

METHOD NAME	DESCRIPTION
copy	Performs a deep copy of a DirectoryMsg .

Table 165: **DirectoryMsg** Utility Methods

8.4.17 Directory Encoding and Decoding

8.4.17.1 Directory Encoding and Decoding Methods

METHOD NAME	DESCRIPTION
encode	Encodes a source directory message. This method takes the EncodeIterator as a parameter into which the encoded content is populated.
decode	Decodes a source directory message. The decoded message may refer to encoded data from the original message. If the message is to be stored for later use, use the copy method of the decoded message to create a full copy.

Table 166: Directory Encoding and Decoding Methods

8.4.17.2 Encoding a Source Directory Request

```

EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
DirectoryRequest directoryRequest = (DirectoryRequest)DirectoryMsgFactory.createMsg();

/* Clear the Directory Request object. */
directoryRequest.clear();

/* Set directory message type - required as object created by DirectoryMsgFactory.createMsg() is generic
   Directory object. */
directoryRequest.rdmMsgType(DirectoryMsgType.REQUEST);

/* Set stream id. */
directoryRequest.streamId(streamId);

/* Set flags indicating presence of optional members. */
directoryRequest.flags(DirectoryRequestFlags.HAS_SERVICE_ID | STREAMING);

/* Set Service ID. */
directoryRequest.serviceId(273);

/* Set service filter. */
directoryRequest.filter(Directory.ServiceFilterFlags.INFO | Directory.ServiceFilterFlags.STATE |
   Directory.ServiceFilterFlags.GROUP);

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
encodeIter.clear();
ret = encodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Encode the message. */
ret = directoryRequest.encode(encodeIter);

```

Code Example 23: Directory Request Encoding Example

8.4.17.3 Decoding a Source Directory Request

```

DecodeIterator decodeIter = CodecFactory.createDecodeIterator();
DirectoryRequest directoryRequest = (DirectoryRequest)DirectoryMsgFactory.createMsg();
Msg msg = CodecFactory.createMsg();

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
decodeIter.clear();

ret = decodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Decode the message to a Msg object. */
ret = msg.decode(decodeIter);

if (ret == CodecReturnCodes.SUCCESS &&
    msg.domainType() == DomainTypes.SOURCE && msg.msgClass() == MsgClasses.REQUEST)
{
    directoryRequest.clear();
    directoryRequest.rdmMsgType(DirectoryMsgType.REQUEST);

    ret = directoryRequest.decode(decodeIter, msg);

    if(ret == CodecReturnCodes.SUCCESS)
    {

        /* Print if Info filter was requested. */
        if ((directoryRequest.filter() & Directory.ServiceFilterFlags.INFO) != 0)
            System.out.println("Info filter requested.");

        /* Print if State filter was requested. */
        if ((directoryRequest.filter() & Directory.ServiceFilterFlags.STATE) != 0)
            System.out.println("State filter requested.");

        /* Print if Group filter was requested. */
        if ((directoryRequest.filter() & Directory.ServiceFilterFlags.GROUP) != 0)
            System.out.println("Group filter requested.");

        /* Print service ID if present. */
        if (directoryRequest.checkHasServiceId())
            System.out.println("Service ID: " + directoryRequest->serviceId);
    }
}

```

Code Example 24: Directory Request Decoding Example

8.4.17.4 Encoding a Source Directory Refresh

```

EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
DirectoryRefresh directoryRefresh = (DirectoryRefresh)DirectoryMsgFactory.createMsg();

/* Clear the Directory Refresh object. */
directoryRefresh.clear();

/* Set directory message type - required as object created by DirectoryMsgFactory.createMsg() is generic
   Directory object. */
directoryRefresh.rdmMsgType(DirectoryMsgType.REFRESH);

/* Set stream id. */
directoryRefresh.streamId(streamId);

/* Set flags for optional members */
directoryRefresh.applySolicited();

/* Set state. */
directoryRefresh.state().streamState(StreamStates.OPEN);
directoryRefresh.state().dataState(DataStates.OK);
directoryRefresh.state().code(StateCodes.NONE);

/* Set filter to say the Info, State, and Group filters are supported. */
directoryRefresh.filter(Directory.ServiceFilterFlags.INFO | Directory.ServiceFilterFlags.STATE |
Directory.ServiceFilterFlags.GROUP);

/* List of services to be used.
 * This example will show encoding of one service. Additional services can be set up using the same method
 * shown below. */
/** Create Service ***/
Service service = CodecFactory.createService();

/** Build Service MY_SERVICE. ***/
service.clear();

/* Set flags to indicate Info and State filter are present. */
service.flags(ServiceFlags.HAS_INFO | ServiceFlags.HAS_STATE);

/* Set action to indicate adding a new service. */
service.info().action(MapEntryActions.ADD);

/* Set flags to indicate optional members. */
service.info().flags(ServiceInfoFlags.HAS_VENDOR | ServiceInfoFlags.HAS_DICTS_PROVIDED |
    ServiceInfoFlags.HAS_DICTS_USED | ServiceInfoFlags.HAS_QOS);

/* Set service name. */
service.info().serviceName().data("MY_SERVICE");

/* Set vendor name. */

```

```

service.info().vendor().data("Refinitiv");

/* Set capabilities list. */
service.info().capabilitiesList().add(DomainTypes.DICTIONARY);
service.info().capabilitiesList().add(DomainTypes.MARKET_PRICE);
service.info().capabilitiesList().add(DomainTypes.MARKET_BY_ORDER);

/* Set dictionaries provided. */
service.info().dictionariesProvidedList().add("RWFFld");
service.info().dictionariesProvidedList().add("RWFEnum");

/* Set dictionaries used. */
service.info().dictionariesUsedList().add("RWFFld");
service.info().dictionariesUsedList().add("RWFEnum");

/* Build QoS list. */
Qos qos1 = CodecFactory.createQos();
qos1.timeliness(QosTimeliness.REALTIME);
qos1.rate(QosRates.TICK_BY_TICK);
Qos qos2 = CodecFactory.createQos();
service.info().qosList().add(qos2);
qos2.timeliness(QosTimeliness.REALTIME);
qos2.rate(QosRates.JIT_CONFLATED);

/* Set QoS list. */
service.info().qosList().add(qos1);
service.info().qosList().add(qos2);

/** Build Service State for MY_SERVICE **/
service.state().flags(ServiceStateFlags.HAS_ACCEPTING_REQS);
service.state().serviceState(1);
service.state().acceptingRequests(1);

/** Finish and encode. **/

/* Set the list of services on the message.*/
directoryRefresh.serviceList().add(service);

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
encodeIter.clear();
ret = encodeIter.setBufferAndRWFVersion(msgBuf, channelMajorVersion, channelMinorVersion);

/* Encode the message. */
ret = directoryRefresh.encode(encodeIter);

```

Code Example 25: Directory Refresh Encoding Example

8.4.17.5 Decoding a Source Directory Refresh

```

DecodeIterator decodeIter = CodecFactory.createDecodeIterator();
DirectoryRefresh directoryRefresh = (DirectoryRefresh)DirectoryMsgFactory.createMsg();
Msg msg = CodecFactory.createMsg();

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
decodeIter.clear();

ret = decodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Decode the message to a Msg object. */
ret = msg.decode(decodeIter);

if (ret == CodecReturnCodes.SUCCESS && msg.domainType() == DomainTypes.SOURCE && msg.msgClass() ==
    MsgClasses.REFRESH)
{
    directoryRefresh.clear();
    directoryRefresh.rdmMsgType(DirectoryMsgType.REFRESH);

    ret = directoryRefresh.decode(decodeIter, msg);

    if(ret == CodecReturnCodes.SUCCESS)
    {
        /* Print serviceId if present. */
        if (directoryRefresh.checkHasServiceId())
            System.out.println("Service ID: " + directoryRefresh.serviceId());

        /* Print information about each service present in the refresh. */
        for(Service service : directoryRefresh.serviceList())
        {
            /* Print Service Info if present */
            if (service.checkHasInfo())
            {
                ServiceInfo info = service.info();

                /* Print service name. */
                System.out.println("Service Name: " + info.serviceName().toString());

                /* Print vendor name if present.*/
                if (info.checkHasVendor())
                    System.out.println("Vendor: " + info.vendor().toString());

                /* Print supported domains if present.*/
                for(long capability : info.capabilityList())
                    System.out.println("Capability: " + DomainTypes.toString(capability));

                /* Print dictionaries provided if present.*/
                if (info.checkHasDictionariesProvided())
                {

```

```
        for (String dictProv : info.dictionariesProvidedList())
            System.out.println("Dictionary Provided: " + dictProv);
    }

    /* Print dictionaries used if present. */
    if (info.checkHasDictionariesUsed())
    {
        for (String dictUsed : info.dictionariesUsedList())
            System.out.println("Dictionary Used: " + dictUsed);
    }

    /* Print qualities of service supported if present. */
    if (info.checkHasQos())
    {
        for (Qos qos : info.qosList())
            System.out.println ("QoS: " + qos.toString());
    }
}

if (service.checkHasState())
{
    ServiceState state = service.state();
    System.out.println("Service state: " + state.serviceState());
    if(state.checkHasAcceptingRequests())
        System.out.println("Accepting Requests: " + state.acceptingRequests());
}
}
```

Code Example 26: Directory Refresh Decoding Example

8.5 RDM Dictionary Domain

The Dictionary domain model conveys information needed for parsing published data. Dictionaries provide additional meta-data, such as that necessary to decode the content of a **FieldEntry** or additional content related to its **fieldId**. For more information about the different types of dictionaries and their usage, refer to the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

This domain's interface makes it easier to use the existing utilities for encoding, decoding, and caching dictionary information. For more information on these utilities, see the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.5.1 Dictionary Request

A **Dictionary Request** message is encoded and sent by OMM consumer applications. This message requests a dictionary from a service.

The **DictionaryRequest** represents all members of a dictionary request message and is easily used in OMM applications that leverage RDMS. This object follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.5.1.1 Dictionary Request Members

MEMBER	DESCRIPTION
dictionaryName	Required . Indicates the name of the dictionary being requested.
flags	Required . Indicates the presence of optional dictionary request members. For details, refer to Section 8.5.1.2.
rdmMsgBase	Required . Specifies the message type (i.e., Dictionary). For a dictionary request, send DictionaryMsgType.REQUEST .
ServiceId	Required . Specifies the service from which to request the dictionary.
verbosity	Required . Indicates the amount of information desired from the dictionary. Available enumerations are: <ul style="list-style-type: none"> • Dictionary.VerbosityValues.INFO = 0x00: Version information only • Dictionary.VerbosityValues.MINIMAL = 0x03: Provides information needed for caching • Dictionary.VerbosityValues.NORMAL = 0x07: Provides all information needed for decoding • Dictionary.VerbosityValues.VERBOSE = 0x0F: Provides all information (including comments) Providers are not required to support the MINIMAL and VERBOSE filters.

Table 167: DictionaryRequest Members

8.5.1.2 Dictionary Request Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
STREAMING	Indicates that the dictionary stream should remain open after the initial refresh. An open stream can listen for status messages that indicate changes to the dictionary version. For more information, see the Enterprise Transport API Java Edition <i>Refinitiv Domain Model Usage Guide</i> .

Table 168: DictionaryRequest Flag

8.5.2 Dictionary Refresh

A **Dictionary Refresh** message is encoded and sent by OMM provider applications. This message transmits dictionary content in response to a request.

The **DictionaryRefresh** represents all members of a dictionary refresh message and is easy to use in OMM applications that leverage RDMs. This object follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.5.2.1 Dictionary Refresh Members

MEMBER	DESCRIPTION
dataBody	When decoding, this points to the encoded data buffer with dictionary content. This buffer should be set on a DecodeIterator and passed to the appropriate decode method according to the type . Not used when encoding. The dictionary is retrieved from the DataDictionary .
dictionary	Conditional (required when encoding). Points to a DataDictionary object that contains content to encode. For more information on the DataDictionary object, refer to the Enterprise Transport API Java Edition <i>Refinitiv Domain Model Usage Guide</i> . Not used when decoding.
dictionaryName	Required . Indicates the name of the dictionary being provided.
flags	Required . Indicates the presence of optional dictionary refresh members. For details, refer to Section 8.5.2.2.
rdmMsgBase	Required . Specifies the message type (i.e., dictionary message). For a dictionary refresh, set to DictionaryMsgType.REFRESH .
sequenceNumber	Optional . A user-specified, item-level sequence number that the application can use to sequence messages in this stream. If present, a flags value of DictionaryRefreshFlags.HAS_SEQ_NUM should be specified.
serviceId	Required . Indicates the service ID of the service from which the dictionary is provided.
startFid	Maintains the state when encoding a dictionary across multiple messages.  Warning! To ensure that all dictionary content is correctly encoded, the application should not modify this.
state	Required . Indicates the state of the dictionary stream. Defaults to a streamState of StreamStates.OPEN and a dataState of DataStates.OK . For more information on State , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 169: DictionaryRefresh Members

MEMBER	DESCRIPTION
dictionaryType	Required . Indicates the type of dictionary being provided. The dictionary encoder and decoder support the following types: <ul style="list-style-type: none"> • <code>Dictionary.VerbosityValues.FIELD_DEFINITIONS = 1</code> • <code>Dictionary.VerbosityValues.ENUM_TABLES = 2</code>
verbosity	Required . Indicates the amount of information desired from the dictionary. Available enumerations are: <ul style="list-style-type: none"> • <code>Dictionary.VerbosityValues.INFO = 0x00</code>: Provides version information only • <code>Dictionary.VerbosityValues.MINIMAL = 0x03</code>: Provides information needed for caching • <code>Dictionary.VerbosityValues.NORMAL = 0x07</code>: Provides all information needed for decoding • <code>Dictionary.VerbosityValues.VERBOSE = 0x0F</code>: Provides all information (including comments) Providers do not need to support the MINIMAL and VERBOSE filters.

Table 169: DictionaryRefresh Members (Continued)

8.5.2.2 Dictionary Refresh Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
<code>DictionaryRefreshFlags.CLEAR_CACHE</code>	Indicates that stored payload information associated with the dictionary stream should be cleared. This might happen if some portion of data is known to be invalid.
<code>DictionaryRefreshFlags.HAS_INFO</code>	Indicates the presence of <code>dictionaryType</code> . Not used when encoding. The <code>encode</code> method adds information to the encoded message when appropriate.
<code>DictionaryRefreshFlags.HAS_SEQ_NUM</code>	Indicates the presence of <code>sequenceNumber</code> .
<code>DictionaryRefreshFlags.IS_COMPLETE</code>	Indicates that this is the final fragment and that the consumer has received all content for this dictionary. Not used when encoding. The <code>encode</code> method adds information to the encoded message when appropriate.
<code>DictionaryRefreshFlags.SOLICITED</code>	Indicates that the directory refresh is solicited (e.g., it is a response to a request). If the flag is not present, this refresh is unsolicited.

Table 170: DictionaryRefreshFlags

8.5.3 Dictionary Status

OMM provider and non-interactive provider applications use the **Dictionary Status** message to convey state information associated with the dictionary stream. Such state information can indicate that a dictionary stream cannot be established or to inform a consumer of a state change associated with an open dictionary stream. The Dictionary status message can also indicate that a new dictionary should be retrieved. For more information on handling Dictionary versions, see the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

The **DictionaryStatus** represents all members of a dictionary status message and allows for simplified use in OMM applications that leverage RDMLs. This object follows the behavior and layout that is defined in the Enterprise Transport API Java Edition *Refinitiv Domain Model Usage Guide*.

8.5.3.1 Dictionary Status Members

MEMBER	DESCRIPTION
flags	Required. Indicate the presence of optional dictionary status members. For details, refer to Section 8.5.3.2.
rdmMsgBase	Required. Specifies the dictionary message type. For a dictionary status, set to <code>DictionaryMsgType.STATUS</code> .
State	Optional. Indicates the state of the dictionary stream. For more information on <code>state</code> , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> . If present, a <code>flags</code> value of <code>DictionaryStatusFlags.HAS_STATE</code> should be specified.

Table 171: DictionaryStatus Members

8.5.3.2 Dictionary Status Flag Enumeration Value

FLAG ENUMERATION	DESCRIPTION
<code>DictionaryStatusFlags.CLEAR_CACHE</code>	Indicates that any stored payload information associated with the dictionary stream should be cleared. This might happen if some portion of data is known to be invalid.
<code>DictionaryStatusFlags.HAS_STATE</code>	Indicates the presence of <code>state</code> . If absent, any previously conveyed state continues to apply.

Table 172: DictionaryStatus Flags

8.5.4 Dictionary Close

A **Dictionary Close** message is encoded and sent by OMM consumer applications. This message allows a consumer to close an open dictionary stream. A provider can close the directory stream via a Dictionary Status message; for details, refer to Section 8.5.3.

MEMBER	DESCRIPTION
rdmMsgBase	Required. Specifies the dictionary message type. For a dictionary close, set to <code>DictionaryMsgType.CLOSE</code> .

Table 173: DictionaryClose Member

8.5.5 Dictionary Messages

DictionaryMsg is the base interface for all Dictionary messages. It is provided for use with general dictionary-specific functionality.

INTERFACE	DESCRIPTION
<code>DictionaryClose</code>	RDM Dictionary Close.
<code>DictionaryRefresh</code>	RDM Dictionary Refresh.
<code>DictionaryRequest</code>	RDM Dictionary Request.
<code>DictionaryStatus</code>	RDM Dictionary Status.

Table 174: DictionaryMsg Interfaces

8.5.6 Dictionary Message: Utility Methods

FUNCTION NAME	DESCRIPTION
copy	Performs a deep copy of a DictionaryMsg object.

Table 175: **DictionaryMsg** Utility Methods

8.5.7 Dictionary Encoding and Decoding

8.5.7.1 Dictionary Encoding and Decoding Methods

METHOD NAME	DESCRIPTION
encode	Encodes a dictionary message. This method takes the <code>EncodeIterator</code> as a parameter into which the encoded content is populated.
decode	Decodes a dictionary message. The decoded message may refer to encoded data from the original message. If the message is to be stored for later use, use the <code>copy</code> method of the decoded message to create a full copy.

Table 176: Dictionary Encoding and Decoding Methods

8.5.7.2 Encoding a Dictionary Request

```

EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
DictionaryRequest dictionaryRequest = (DictionaryRequest)DictionaryMsgFactory.createMsg();

/* Clear the Dictionary Request object. */
dictionaryRequest.clear();

/* Set dictionary message type - required as object created by DictionaryMsgFactory.createMsg() is
   generic Dictionary object. */
dictionaryRefresh.rdmMsgType(DictionaryMsgType.REQUEST);

/* Set stream id. */
dictionaryRefresh.streamId(streamId);

/* Set streaming flag. */
dictionaryRequest.applyStreaming();

/* Set serviceId. */
dictionaryRequest.serviceId(273);

/* Set verbosity. */
dictionaryRequest.verbosity(Dictionary.VerbosityValues.NORMAL);

/* Set dictionary name. */
dictionaryRequest.dictionaryName().data("RWFFld");

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
encodeIter.clear();
ret = encodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

```

```
/* Encode the message. */
ret = dictionaryRequest.encode (encodeIter) ;
```

Code Example 27: Dictionary Request Encoding Example

8.5.7.3 Decoding a Dictionary Request

```

DecodeIterator decodeIter = CodecFactory.createDecodeIterator();
DictionaryRequest dictionaryRequest = (DictionaryRequest)DictionaryMsgFactory.createMsg();
Msg msg = CodecFactory.createMsg();

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
decodeIter.clear();
ret = decodeIter.setBufferAndRWFVersion(msgBuf,channelMajorVersion, channelMinorVersion);

/* Decode the message to a Msg object. */
ret = msg.decode(decodeIter);

if (ret == CodecReturnCodes.SUCCESS && msg.domainType() == DomainTypes.DICTIONARY && msg.msgClass() ==
    MsgClasses.REQUEST)
{
    dictionaryRequest.clear();

/* Set dictionary message type - required as object created by DictionaryMsgFactory.createMsg() is
   generic Dictionary object. */
dictionaryRequest.rdmMsgType(DictionaryMsgType.REQUEST);

    ret = dictionaryRequest.decode(decodeIter, msg);

    if(ret == CodecReturnCodes.SUCCESS)
    {
        if(dictionaryRequest.checkStreaming())
            System.out.println("Request is streaming");

        /* Print serviceId. */
        System.out.println ("Service ID: " + dictionaryRequest.serviceId());

        /* Print verbosity. */
        System.out.println ("Verbosity: " + dictionaryRequest.verbosity());

        /* Print dictionary name. */
        System.out.println ("Dictionary Name: " + dictionaryRequest.dictionaryName().toString());
    }
}

```

Code Example 28: Dictionary Request Decoding Example

8.5.7.4 Encoding a Dictionary Refresh

```

EncodeIterator encodeIter = CodecFactory.createEncodeIterator();
DictionaryRefresh dictionaryRefresh = (DictionaryRefresh)DictionaryMsgFactory.createMsg();

/* Clear the Dictionary Refresh object. */
dictionaryRefresh.clear();
dictionaryRefresh.rdmMsgType(DictionaryMsgType.REFRESH);

DataDictionary dataDictionary = CodecFactory.createDataDictionary();
dataDictionary.clear();

ret = dataDictionary.loadFieldDictionary("RDMFieldDictionary", errorText);

/* Clear the Dictionary Refresh object. */
dictionaryRefresh.clear();

/* Set dictionary message type - required as object created by DictionaryMsgFactory.createMsg() is
   generic Dictionary object. */

dictionaryRefresh.rdmMsgType(DictionaryMsgType.REFRESH);

/* Set stream id. */
dictionaryRefresh.streamId(streamId);

/* Set state fields to state object managed by dictionary refresh. */
dictionaryRefresh.state().streamState(StreamStates.OPEN);
dictionaryRefresh.state().dataState(DataStates.OK);
dictionaryRefresh.state().code(StateCodes.NONE);

/* Set flags. */
dictionaryRefresh.applySolicited();

/* Set dictionary name. */
dictionaryRefresh.dictionaryName().data("RWFFld");

/* Set dictionary type. */
dictionaryRefresh.dictionaryType(Dictionary.Types.FIELD_DEFINITIONS);

/* Set the dictionary. */
dictionaryRefresh.dictionary(dataDictionary);

/* Set serviceId. */
dictionaryRefresh.serviceId(273);

/* Set verbosity. */
dictionaryRefresh.verbosity(Dictionary.VerbosityValues.NORMAL);

do
{

```

```

/* (Represents the application getting a new buffer to encode the message into.) */
getNextEncodeBuffer(msgBuffer);

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
encodeIter.clear();
ret = encodeIter.setBufferAndRWFVersion(msgBuf, channelMajorVersion, channelMinorVersion);

/* Encode the message. This will return CodecReturnCodes.DICT_PART_ENCODED if it only a part
 * was encoded. We must keep encoding the message until CodecReturnCodes.SUCCESS is returned. */
ret = dictionaryRefresh.encode(encodeIter);
} while (ret == CodecReturnCodes.DICT_PART_ENCODED);

```

Code Example 29: Dictionary Refresh Encoding Example**8.5.7.5 Decoding a Dictionary Refresh**

```

DecodeIterator decodeIter = CodecFactory.createDecodeIterator();
DictionaryRefresh dictionaryRefresh = (DictionaryRefresh)DictionaryMsgFactory.createMsg();
Msg msg = CodecFactory.createMsg();

DataDictionary dataDictionary = CodecFactory.createDataDictionary();
dataDictionary.clear();

int dictionaryTypeForThisStreamId = 0;

do
{
    /* (Represents the application getting the next buffer to decode.) */
    getNextDecodeBuffer(msgBuf);

    /* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
    decodeIter.clear();
    ret = decodeIter.setBufferAndRWFVersion(msgBuf, channelMajorVersion, channelMinorVersion);

    /* Decode the message to a Msg object. */
    sret = msg.decode(decodeIter);
    if (ret == CodecReturnCodes.SUCCESS && msg.domainType() == DomainTypes.DICTIONARY && msg.msgClass()
        == MsgClasses.REFRESH)
    {
        dictionaryRefresh.clear();

        /* Set dictionary message type - required as object created by DictionaryMsgFactory.createMsg()
           is generic Dictionary object. */
        dictionaryRefresh.rdmMsgType(DictionaryMsgType.REFRESH);

        ret = dictionaryRefresh.decode(decodeIter, msg);

        if(ret == CodecReturnCodes.SUCCESS)
        {

```

```

/* Print if request is streaming. */
if (dictionaryRefresh.checkSolicited())
    System.out.println("Refresh is solicited.");

/* Print info if present. If the dictionary is split into parts, this is normally only
   present on the first part. */
if (dictionaryRefresh.checkHasInfo())
{
    /* Remember the dictionary type for this stream since subsequent parts will not indicate
       it. */
    dictionaryTypeForThisStreamId = dictionaryRefresh.dictionaryType();

    /* Print version. */
    System.out.println("Version: " + dictionaryRefresh.version.toString());

    /* Print dictionary ID. */
    System.out.println("Dictionary ID: " + dictionaryRefresh.dictionaryId());
}

/* Print serviceId. */
System.out.println("Service ID: " + dictionaryRefresh.serviceId());

/* Print verbosity. */
System.out.println("Verbosity: " + dictionaryRefresh.verbosity());

/* Print dictionary name. */
System.out.println("Dictionary Name: " + dictionaryRefresh.dictionaryName().toString());

if (dictionaryTypeForThisStreamId == Dictionary.Types.FIELD_DEFINITIONS)
{
    /* Decode the dictionary content into the DataDictionary object. */
    decodeIter.clear();
    ret = decodeIter.setBufferAndRWFVersion(dictionaryRefresh.dataBody(),
                                              channelMajorVersion, channelMinorVersion);

    ret = dataDictionary.decodeFieldDictionary(decodeIter,
                                               Dictionary.VerbosityValues.NORMAL, errorText);
}
}

}

}

} while(!(dictionaryRefresh.checkRefreshComplete()));

```

Code Example 30: Dictionary Refresh Decoding Example

8.6 RDM Queue Messages

The Queue Messaging domain model is a series of message constructs that you use to interact with a Queue Provider. A Queue Provider can persist content for which users want to have guaranteed delivery and can also help send content to destinations with which users cannot directly communicate.

8.6.1 Queue Data Message Persistence

When opening a queue messaging stream with a queue provider, using a persistence file can guarantee delivery of messages sent by the OMM consumer on that queue stream. The queue file will be named after the name of the queue stream (as specified in the `QueueRequest` message that opened the stream). When the consumer submits `QueueData` messages, the consumer stores these messages in the persistence file in case the tunnel stream to the queue provider is lost and reconnected. As `QueueAck` messages are received from the queue provider, space in the persistence file is freed for additional messages. If at any time the application submits an `QueueData` message but the persistence file has no room for it, the application receives the `ReactorReturnCodes.PERSISTENCE_FULL` return code.

The `ClassOfService.guarantee.persistLocally` option (set when opening the tunnel stream) specifies whether to create and maintain persistence files. The location for storage of persistent files is specified by the `ClassOfService.guarantee.persistenceFilePath` option. For more information on these options, refer to Section 6.8.3.

NOTE: Refinitiv recommends that the `ClassOfService.guarantee.persistenceFilePath` be set to a local storage device.

If a particular queue stream is no longer needed, the user may delete the persistence file that carries the associated queue stream's name.

 **Warning!** If you delete a persistence file that stores messages that were not successfully transmitted, the messages will be lost.

8.6.2 Queue Request

The OMM application encodes and sends a `Queue Request` message to a Queue Provider to open a user queue. By opening a queue with an `QueueRequest`, the user receives any content previously sent to and persisted on a Queue Provider. To send content to another user's queue, a user must first open their own queue.

MEMBER	DESCRIPTION
rdmMsgBase	Required. Specifies the message type. For a queue request, use <code>QueueMsgType.REQUEST</code> .
sourceName	Required. Specifies the name of the queue you want to open.

Table 177: `QueueRequest` Members

8.6.3 Queue Refresh

A Queue Provider encodes and sends a **Queue Refresh** message to OMM applications to inform users about queue open requests and give state information pertaining to specific queue refresh request attempts.

MEMBER	DESCRIPTION
rdmMsgBase	Required. Sets the message type. For a queue refresh, use QueueMsgType.REFRESH .
sourceName	Required. Specifies the name of a queue you want to open.
state	Required. Indicates the state of the queue. <ul style="list-style-type: none"> States of Open and Ok indicate the queue was successfully opened. Other state combinations indicate an issue, for which additional code and text provide supplemental information. For more information on State , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .
queueDepth	Required. Indicates the number of messages remaining in the queue for this stream.

Table 178: QueueRefresh Members

8.6.4 Queue Status

A Queue Provider encodes and sends **Queue Status** messages to OMM applications, conveying state information about a user's queue.

MEMBER	DESCRIPTION
flags	Required. Indicates the presence of optional queue status members. flags has only one enumeration: HAS_STATE , which indicates the presence of the state member. If flags is absent (or has no value), any previously conveyed state continues to apply.
rdmMsgBase	Required. Sets the message type. For a queue status, use QueueMsgType.STATUS .
state	Indicates the state of the queue: <ul style="list-style-type: none"> States of Open and Ok indicate the queue is in a good state. Other state combinations indicate an issue, for which additional code and text provide supplemental information. For more information on State , refer to the Enterprise Transport API Java Edition <i>Developers Guide</i> .

Table 179: QueueStatus Members

8.6.5 Queue Close

An OMM application encodes and sends a **Queue Close** message to a Queue Provider, closing the user's queue.

MEMBER	DESCRIPTION
rdmMsgBase	Required. Sets the message type. For a queue close, use QueueMsgType.CLOSE .

Table 180: QueueClose Members

8.6.6 Queue Data

Both OMM applications and queue providers can send and receive **Queue Data** messages, which exchange data content between queue users and also communicate whether content was undeliverable.

8.6.6.1 Queue Data Members

MEMBER	DESCRIPTION
containerType	Required . Indicates the type of contents in this queue data message.
destName	Required . Specifies the name of the queue to which content is sent.
encodedDataBody	Optional. <ul style="list-style-type: none"> If sending a message, populate encodedDataBody with pre-encoded content. If sending a message without pre-encoded contents, you can use the encoding methods described in Section 8.6.6.4. If receiving a message, encodedDataBody can be used to access payload contents for decoding.
flags	Required . Specifies any flags that indicate more information about this message. For further details on available flags, refer to Section 8.6.6.2.
identifier	Required . A user-specified unique identifier for the message being sent. identifier is used when acknowledging this content via a Queue Ack message.
queueDepth	Required . Indicates the number of Queue Data or Queue Data Expired messages still inbound on this queue stream, following this message.
rdmMsgBase	Required . Sets the message type. For queue data, use QueueMsgType.DATA .
sourceName	Required . Specifies the name of the queue from which content is sourced, which should match the sourceName specified in the Queue Request for this substream.
timeout	Optional . Specifies the desired timeout for this content (which can be any of the QueueMsgTimeoutCodes in Section 8.6.6.3 or a specific time interval in milliseconds). If a timeout value expires during the course of delivery, the content is returned as a QueueDataExpired message. If not specified, this defaults to QueueMsgTimeoutCodes.INFINITE (i.e., the content never times out).

Table 181: QueueData Members

8.6.6.2 Queue Data Flag

QueueData messages and **QueueDataExpired** messages use the following flag:

FLAG	DESCRIPTION
QueueDataFlags.POSSIBLE_DUPLICATE= 0x1	Indicates that the message was retransmitted and that the application might have already received it.

Table 182: Queue Data Flag

8.6.6.3 Queue Message Timeout Codes

ENUMERATION	DESCRIPTION
INFINITE	This message persists in the system for an infinite amount of time.
IMMEDIATE	This message immediately times out if any portion of its delivery path is unavailable.
PROVIDER_DEFAULT	This message persists in the system for a duration set by the provider.

Table 183: Queue Data Message Timeout Codes

8.6.6.4 Queue Data Encoding

METHOD NAME	DESCRIPTION
encode	When sending no payload or payload content is preencoded and specified on the <code>QueueData.encodedDataBody</code> buffer, this method encodes the <code>QueueData</code> message in a single call.
encodeComplete	Completes the content encoding into this <code>QueueData</code> message.
encodeInit	Begins the process of encoding content into this <code>QueueData</code> message. This method takes an <code>EncodeIterator</code> as a parameter, where the <code>EncodeIterator</code> is associated with the buffer into which content is encoded. When this method returns, users should call additional methods required to encode the content. After all remaining encoding is completed, call the <code>encodeComplete</code> method.

Table 184: Queue Data Message Encoding Methods

8.6.6.5 Queue Data Message Encoding Code Sample

```

EncodeIterator _msgEncIter = CodecFactory.createEncodeIterator();
QueueData _queueData = QueueMsgFactory.createQueueData();

// initialize the QueueData encoding
_queueData.clear();
_queueData.streamId(QUEUE_MSG_STREAM_ID);
_queueData.identifier(124);
_queueData.sourceName().data("MY_QUEUE");
_queueData.destName().data("DESTINATION_QUEUE");
_queueData.timeout(QueueMsgTimeoutCodes.INFINITE);
_queueData.containerType(DataTypes.FIELD_LIST);

_msgEncIter.clear();
_msgEncIter.setBufferAndRWFVersion(buffer, tunnelStream.classOfService().common().
    protocolMajorVersion(), tunnelStream.classOfService().common().protocolMinorVersion());

// begin encoding content into QueueData message
if ((ret = _queueData.encodeInit(_msgEncIter)) < ReactorReturnCodes.SUCCESS)
{
    System.out.println("QueueData.encodeInit() failed");
    return;
}

// Start Content Encoding - follow standard field list encoding
// as shown in the Transport API Java Developers Guide examples

// when content encoding is done, complete the QueueData encoding
if ((ret = _queueData.encodeComplete(_msgEncIter)) < ReactorReturnCodes.SUCCESS)
{
    System.out.println("QueueData.encodeComplete() failed");
    return;
}

```

Code Example 31: Queue Data Message Encoding Example

8.6.7 QueueDataExpired

If queue data messages sent on a queue stream cannot be successfully delivered, the queue provider sends **QueueDataExpired** messages on the queue stream to OMM consumer applications.

OMM consumer applications do not send this message.

8.6.7.1 QueueDataExpired Members

MEMBER	DESCRIPTION
containerType	Required . Indicates the type of contents in the message.
destName	Required . <code>destName</code> specifies the name of the queue from which content is sourced (i.e., the value of <code>sourceName</code> as set in the original QueueData message).
encodedDataBody	Optional. Contains the payload contents (if any) of the original Queue Data message.
flags	Required . <code>flags</code> indicate more information about this message. For details, refer to Section 8.6.6.2.
identifier	Required . A user-specified, unique identifier for the message (which is the same as the <code>identifier</code> from the original QueueData message).
queueDepth	Required . Indicates how many Queue Data or Queue Data Expired messages are still inbound on this queue stream (following this message).
rdmMsgBase	Required . Specifies the queue message type. For expired queue data, use <code>QueueMsgType.DATAEXPIRED</code> .
sourceName	Required . <code>sourceName</code> specifies the name of the queue to which content was sent (i.e., the value of <code>destName</code> as set in the original QueueData message).
undeliverableCode	Required . Specifies a code explaining why the content was undeliverable. For more information on undeliverable codes and their meanings, refer to Section 8.6.7.2.

Table 185: QueueDataExpired Members

8.6.7.2 Queue Data Message Undeliverable Codes

ENUMERATION	REASON FOR DELIVERY FAILURE
EXPIRED	Indicates that the timeout value specified for this message has expired.
INVALID_SENDER	Indicates that the sender of this message has now become invalid.
INVALID_TARGET	Indicates that the specified destination of this message does not exist.
MAX_MSG_SIZE	Indicates that the message was too large.
NO_PERMISSION	Indicates that the source/sender of this message is not permitted to send or is not permitted to send to the specified destination.
QUEUE_DISABLED	Indicates that the specified destination of this message has a disabled queue.
QUEUE_FULL	Indicates that the specified destination of this message has a full queue and cannot receive any additional content.
TARGET_DELETED	Indicates that the target queue was deleted after sending the message, but before the message was delivered.

Table 186: Queue Data Message Undeliverable Codes

8.6.8 Queue Ack

A Queue Provider encodes and sends a **Queue Ack** message to OMM applications, acknowledging that a Queue Data message is persisted on the Queue Provider. After a Queue Provider acknowledges persistence, the application no longer needs to persist the acknowledged content.

MEMBER	DESCRIPTION
destName	Required . Specifies the name of the queue from which content is sourced (i.e., the value of <code>sourceName</code> as set in the original Queue Data message).
identifier	Required . The identifier of the message being acknowledged. This should match the <code>QueueData.identifier</code> for the message being acknowledged.
sourceName	Required . Specifies the name of the queue to which content was originally sent (i.e., the value of <code>destName</code> as set in the original Queue Data message).
rdmMsgBase	Required . Sets the message type. For a queue ack, this is set to <code>QueueMsgType.ACK</code> .

Table 187: Queue Ack Members

9 Warm Standby Feature

9.1 Overview

The Warm Standby feature is implemented at the Value Add Watchlist layer of Enterprise Transport API and is client-side feature. This feature works by providing the application the capability to failover from an active to one or more standby server(s) in the event that the primary/active fails. Application must configure the active and standby servers to use this API feature. After the connections are established with the provided servers which form a Warm Standby group, the client-side or consumer sends messages to the standby server connections to change their mode to Standby. Requested items are opened on all servers by the consumer but the active server responds with messages such as refresh, updates, status, etc. to the consumer. Standby servers respond with blank/empty refreshes. When primary fails, consumer notifies the next server in standby list that it is now Active. The new active server responds with refresh as needed resumes updates for all open items. This process of cut-over is transparent to the application.

The watchlist feature must be enabled to use the Warm Standby feature. A server qualifies to be a standby only if it advertises support for Warm Standby, supports similar features over login and offers an identical service (supported domains, quality of service, etc.) as the active server.

Warm Standby not only reduces overall recovery time, but also network traffic by not inducing a “packet storm” with a flurry of re-requests to a standby server. Because the standby server is already aware of items an application has subscribed for, during a failover Enterprise Transport API does not need to re-subscribe open items between a provider and consumer.

9.2 Warm Standby Modes

The Enterprise Transport API Value Add layer supports two Warm Standby modes:

- Login based Warm Standby
- Service based Warm Standby

The login based Warm Standby uses the connection lost event to switch from a primary server to a standby server from the standby server list. The service based Warm Standby uses the service down event OR connection lost event to switch all subscribe items from a primary service to a standby service.

The service based Warm Standby mode offers better resiliency than the login based mode as it can switch from primary to standby if an upstream service is down but the connection to both servers remains intact. A particular server may be the primary for one service and standby for another service as a result. This ability to failover in the event of service down or channel down events makes the service based Warm Standby the recommended mode.

The following figure illustrates the sequence of events when using the Login Based Warm Standby feature:




Figure 12. Login Based Warm Standby Order of Events in a Cutover from Active to Standby

The following figure illustrates the sequence of events when using the Service Based Warm Standby feature:




Figure 13. Service Based Warm Standby Order of Events in a Cutover from Active to Standby

9.3 Warm Standby Configuration and Feature Details

Application written to the Enterprise Transport API VA layer with watchlist enabled may be configured to use a particular stand by mode. Application must configure a group of servers, or Warm Standby group in which a starting active server and one or more standby servers are specified. Using this configuration, the Enterprise Transport API library will internally request the same items from both active and standby servers.

For the sample code for specifying a starting active server and a standby server, see Section 9.3.1.

The consumer application receives updates only on the item streams opened on the active server or active service; it does not get updates, status, unsolicited refreshes, and Generic Messages from the standby servers(s) or standby service(s). If the active server or active service is down, Enterprise Transport API notifies one of the standby servers that it is a new active for the requested service. The new active then begins sending data without the consumer application needing to re-request the items. After cut-over, the new active responds by sending

any conflated updates containing all changed data for conflatable domains and sending unsolicited refresh messages followed by updates for any non-conflated domains. This process brings active data streams back to their pre-failover state.

If the failed server or service comes back online, Enterprise Transport API does not switch back to it. It becomes one of the servers in the standby list. Internally, the Enterprise Transport API consumer-side sends a *ConsumerConnectionStatus GenericMsg* on the Login domain for login based and on the Directory domain for service based to indicate to the provider applications whether they should operate as an active server or service based on the Warm Standby mode. Refer to the *RDM Usage Guide* for more details on this message on the Login and Directory domains.

After establishing a connection to the standby server, Enterprise Transport API internally obeys the following rules for Warm Standby:

- The Standby server's login response must match the following login elements and state support for standby and the same standby mode as active server:
 - **ApplicationId**
 - **PositionId**
 - **ProvidePermissionProfile**: If requested by the user, the values received from all servers must match what was requested.
 - **ProvidePermissionExpressions**: If requested by the user, the values received from all servers must match what was requested.
 - **SingleOpen**
 - **AllowSuspectData**
 - **SupportPost**
 - **SupportBatchRequests**
 - **SupportOMMPost**
 - **SupportStandby**
 - **SupportViewRequests**

If any of these elements does not match, then Enterprise Transport API disconnects the standby server.

- The standby server's Directory response must match all attributes except **Vendor** and **IsSource** of the Directory Info Filter for services common to both active and standby servers. Otherwise Enterprise Transport API disconnects the standby server.
- The standby server's Dictionary response must match the major version. Otherwise Enterprise Transport API disconnects the standby server.
- The provider application can optionally send the **SupportStandbyMode** element in login response to advertise supported Warm Standby mode to consumer applications. Enterprise Transport API disconnects the server if the mode does not match with the configured Warm Standby mode on consumer side.
- Enterprise Transport API routes Generic Messages only on streams in administrative domains. Generic Message on data streams is not routed to the standby server(s).
- Post Message is routed to the active and all standby servers to ensure data on all servers is synchronized.

If the active server or service fails when switching to the new active server or service, Enterprise Transport API does the following:

- For all services that were offered by the old active server but are not offered by the new active server, Enterprise Transport API sends a directory update message stating that the service is down for login based.
- For an item on the failed server but no longer open on the newly active server, Enterprise Transport API sends an internally-generated status message with the *ClosedRecover* stream state to the consumer application.

9.3.1 Configuration Example for a Starting Server and a Standby Server

```
ReactorWarmStandbyGroup reactorWarmStandbyGroup = ReactorFactory.createReactorWarmStandbyGroup();
ReactorWarmStandbyServerInfo standbyServerInfo = ReactorFactory.createReactorWarmStandbyServerInfo();
ReactorConnectOptions reactorConnectOpts = ReactorFactory.createReactorConnectOpts();

reactorWarmStandbyGroup.startingActiveServer().reactorConnectInfo().connectOptions().connectionType(ConnectionTypes.SOCKET);
reactorWarmStandbyGroup.startingActiveServer().reactorConnectInfo().connectOptions().unifiedNetworkInfo().address("dataserver1");
reactorWarmStandbyGroup.startingActiveServer().reactorConnectInfo().connectOptions().unifiedNetworkInfo().serviceName("14002");

standbyServerInfo.reactorConnectInfo().connectOptions().connectionType(ConnectionTypes.SOCKET);
standbyServerInfo.reactorConnectInfo().connectOptions().unifiedNetworkInfo().address("dataserver2");
standbyServerInfo.rreactorConnectInfo().connectOptions().unifiedNetworkInfo().serviceName("14002");

reactorWarmStandbyGroup.standbyServerList().add(standbyServerInfo);
reactorWarmStandbyGroup.warmStandbyMode(ReactorWarmStandbyMode.SERVICE_BASED);
reactorConnectOpts.reactorWarmStandbyGroupList.add(reactorWarmStandbyGroup);
```

Example 32: Warm Standby Configuration Example

9.4

10 Payload Cache Detailed View

10.1 Concepts

The Value Added Payload Cache component provides a facility for storing OMM containers (the message's data payload). Typical use of a payload cache is to store the current image of OMM data streams, where each entry in the cache corresponds to a single data stream. The initial content of a cache entry is defined by the payload of a refresh message. The current (or last) value of the entry is defined by the cumulative application of all refresh and update messages applied to the cache entry container. Values are stored in and retrieved from the cache as encoded OMM containers.

A cache is defined as a collection of OMM data containers. An application may create multiple cache collections, or instances, depending on how it wants to organize the data. The only restriction on cache organization is that all entries in a cache must use the same RDM Field Dictionary to define the set of field definitions it will use. At minimum, a separate cache would be required for each field dictionary in use by the application. However, because cache instances can also share the same field dictionary, partitioning is not restricted to dictionary usage. Some examples of how cache instances can be organized in an application include: all item streams on a connection; all items belonging to a particular service; all items across the entire application.

The application is responsible for organizing cache instances, managing the lifecycle of all entries in each cache, and applying and retrieving data from the cache. Figure 14 shows an example consumer type application which has created two cache instances to store data from two services on an OMM provider.




Figure 14. Consumer Application using Cache to Store Payload Data for Item Streams

10.2 Payload Cache

This section describes how the payload cache is managed (initialization and uninitalization), and how instances of cache (collections of payload entries) are created and destroyed.

10.2.1 Payload Cache Management

After the first Value Added Payload Cache instance is created, all global static resources used by the cache are initialized. When the application destroys the last cache instance, the cache releases all the resources it used.

10.2.2 Cache Error Handling

Some of the methods on the payload cache interface use the **CacheError** object to return error information. This object will be populated with additional information if an error occurs during the method call. The application should check the return value from methods. The application can optionally provide the **CacheError** object to obtain additional information.

10.2.2.1 Cache Error Class Members

The **CacheError** has the following class members:

CLASS MEMBER	DESCRIPTION
errorId	Specifies an error ID. The range of values is defined by the set of Enterprise Transport API Codec return codes (from the CodecReturnCodes enumeration).
text	This String will contain text with additional information when a method call returns a failed result.

Table 188: CacheError Class Members

10.2.2.2 Clearing a Cache Error

The following method clears the **CacheError**.

METHOD NAME	DESCRIPTION
clear	Clears the CacheError object. Use this method prior to passing the object to a cache interface method.

Table 189: CacheError Utility Method

10.2.3 Payload Cache Instances

A payload cache instance is a collection of payload data containers. An empty cache instance must be created before any data can be stored in the cache. When a cache or its entries are no longer needed, it can be destroyed. For methods used to create and destroy a cache, refer to Section 10.2.3.1.

10.2.3.1 Managing the Payload Cache Instance

METHOD NAME	DESCRIPTION
CacheFactory.createPayloadCache	Creates a payload cache instance. Options are passed in via the PayloadCacheConfigOptions whose member is defined in Section 10.2.3.2.
destroy	Destroys a payload cache instance. Any entries remaining in the cache are also destroyed at this time.
destroyAll	Destroys all payload cache instances. All entries remaining in the application are also destroyed at this time.

Table 190: Methods for Managing Cache Instances

10.2.3.2 Payload Cache Config Options

MEMBER	DESCRIPTION
maxItems	Sets the maximum number of entries allowed in the cache. When the maximum number of items is reached, the cache refuses new entries until existing entries are removed. The CacheFactory.createPayloadEntry method will return a null PayloadEntry when the maximum number of items is reached. When set to zero, the cache allows an unlimited number of items. Refer to Section 10.3.1.

Table 191: **PayloadCacheConfigOptions** Members

10.2.4 Managing RDM Field Dictionaries for Payload Cache

Each cache instance requires an RDM Field Dictionary, to define the set of fields that may be encoded in the OMM containers stored in the cache.

A cache is associated with a field dictionary through a setting process, which requires a **DataDictionary** object loaded with the field dictionary. The dictionary object can be loaded from a file (using the **loadFieldDictionary** method) or from an encoded dictionary message from a provider (using the **decodeFieldDictionary** method). The cache does not use the enumerated dictionary content, so loading the enumeration dictionary is not required. For more information on using **DataDictionary**, refer to the *Enterprise Transport API Reference Manual*.

After the **DataDictionary** loads, it is set to a cache instance using a key (an arbitrary string identifier assigned by the application to name the dictionary). The key allows multiple cache instances to share the same dictionary. After the first setting of a dictionary, it can be set to additional cache instances by simply providing the same key on additional settings. For a list of methods used in setting a dictionary to a cache, refer to Section 10.2.4.1.

The cache builds its own field definition database from the **DataDictionary** definitions. After setting, the application does not need to retain the dictionary object, because the cache does not refer to the **DataDictionary** used during the setting. In typical usage, the application will likely retain the dictionary for use with other encoding and decoding operations.

NOTE: A cache can be set to a dictionary only once during its lifetime. While a cache cannot be switched to a new dictionary, the dictionary in use can be extended with new definitions. Refer to Section 10.2.4.3.

10.2.4.1 Setting Functions

METHOD NAME	DESCRIPTION
setDictionary	<p>This method sets a DataDictionary to a cache instance. Use this method the first time a dictionary is set to a cache. The application must provide a key parameter to this method to name the dictionary for future reference. This key is used in future setting operations when the application wants to share a dictionary between cache instances or to extend the definitions in the dictionary.</p> <p>The first time a particular key is used with this method will be the initial setting of that dictionary to a cache. The second time the same key is used in this method; it will reload the field definitions from the given DataDictionary object, enabling the dictionary to be extended. Refer to Section 10.2.4.3.</p>
setSharedDictionaryKey	<p>Use this method when sharing a dictionary among multiple caches. This method sets a cache (identified by the dictionary key name) to a previously set dictionary (identified by the dictionary key name). To share a dictionary, the dictionary must have previously had an initial setting to another cache using the setDictionary method.</p> <p>This method does not require the DataDictionary object, since that was already loaded during the initial setting with this dictionary key.</p>

Table 192: Methods for Setting Dictionary to Cache

10.2.4.2 Setting Example

In the following example, two cache instances are created and set to a single, shared field dictionary.

```

PayloadCacheConfigOptions cacheConfig = CacheFactory.createPayloadCacheConfig();
cacheConfig.maxItems(0); /* unlimited */

/* For simplicity in this code fragment, CHK is assumed to be a macro for error handling (performing
cleanup and returning from method). */

/* create cache instances */
CacheError cacheError = CacheFactory.createCacheError();
PayloadCache cacheInstance1 = CacheFactory.createPayloadCache(cacheConfig, cacheError);
if (cacheInstance1 == null)
{
    System.out.println("CacheFactory.createPayloadCache failure: " + cacheError.text());
    CHK(cacheError.errorId());
}

PayloadCache cacheInstance2 = CacheFactory.createPayloadCache(cacheConfig, cacheError);
if (cacheInstance2 == null)
{
    System.out.println("CacheFactory.createPayloadCache failure: " + cacheError.text());
    CHK(cacheError.errorId());
}

/* Load an RDM Field Dictionary object from file: set to each cache. */
DataDictionary dataDictionary = CodecFactory.createDataDictionary();

```

```

com.refinitiv.eta.transport.Error error = TransportFactory.createError();
int ret = dataDictionary.loadFieldDictionary("RDMFieldDictionary", error); CHK(ret);

String dictionaryKey = "SharedKey1";

/* Initial setting of the dictionary to the first cache */
ret = cacheInstance1.setDictionary(dataDictionary, dictionaryKey, cacheError); CHK(ret);
/* Shared setting of the same dictionary to the second cache */
ret = cacheInstance2.setSharedDictionaryKey(dictionaryKey, cacheError); CHK(ret);
/* The dataDictionary can be destroyed after setting, but is typically retained by the application for
   encoding and decoding. */

/* Two cache instances are now ready for applying and retrieving data */

/* Cleanup */
cacheInstance1.destroy(); /* destroys all entries and the cache instance */
cacheInstance2.destroy();

```

Code Example 33: Creating Cache and Setting to Dictionary

10.2.4.3 Extending the Cache Field Dictionary

While a cache can only be set to a single dictionary during its lifetime, the set of field definitions defined by the dictionary can be extended. This is accomplished by reloading the cache field definition database with another call to the **setDictionary** method. When extending the field dictionary, the **DataDictionary** must contain the original field definitions and any new definitions the application wishes to use. Changes or deletions to the original field definitions are not supported; only additions are allowed. Using the same **PayloadCache** instance and dictionary key that were previously set, call the **setDictionary** method again with extended dictionary object.

NOTE: When extending a field dictionary that is shared, all caches sharing that same dictionary key will see the extension with only a single call to **setDictionary**. There is no need to set the shared dictionary key again to each cache after a dictionary is extended.

10.2.5 Payload Cache Utilities

Use the following methods for managing cache instances. These utilities provide a count of the cache entries and a list of handles to each cache entry.

METHOD NAME	DESCRIPTION
entryCount	Returns the number of item payload entries in this cache instance
entryList	Populates an array list for this cache instance. Because each cache entry is likely associated with an entry in the application's item list, an application would typically manage the entire set of entry instances. This utility provides access to the entire entry instance list if needed.
clear	Destroys all entries in the cache instance. The empty cache can be reused and remains bound to it's data dictionary.

Table 193: **PayloadCache** Utility Methods

10.3 Payload Cache Entries

A payload cache entry stores a single OMM container (whose containers are defined by **DataTypes**). While a cache entry can store any arbitrary OMM data, the primary use case is to maintain the last known value of an item data stream by applying the sequence of refresh and update messages in the stream to the cache entry. Initial data applied to a container must be a refresh message payload, which will define the container type to be stored (e.g. Map). As refresh and update messages from the item stream are applied to the cache entry, the cache decodes the OMM data and sets the current value by following the OMM rules for the container (e.g., adding, deleting, or updating map entries in a Map, or updating fields in a field list). The last value of the data stream can be retrieved from cache at any time as an encoded OMM container.

10.3.1 Managing Payload Cache Entries

Payload cache entries are created within a cache instance. Use the **CacheFactory.createPayloadEntry** method to create a cache entry instance. You cannot move entries between different cache instances, due to their dependency on the field dictionary set to the cache where they are created.

Cache entries only store the payload container of an item. Maintain other item data (e.g. message key attributes, domain, state) as needed in an item list managed by the application, which will identify the source or sink associated with the cache entry data. This item list will likely include the **PayloadEntry** instance if the payload of the item is cached.

For a list of basic utilities provided by the payload cache to manage the collection of entries in the cache, refer to Section 10.2.5.

Use the following methods to manage cache entries:

METHOD NAME	DESCRIPTION
CacheFactory.createPayloadEntry	This method returns a newly created entry in the cache defined by the given PayloadCache instance. This method will return a null instance if it cannot create the entry (e.g., if the maximum number of entries as defined in PayloadCacheConfigOptions would be exceeded).
destroy	This method destroys the cache entry defined PayloadEntry instance and removes it from its cache.
clear	This method deletes any data in the cache entry instance and returns the entry to its initial state. The entry itself remains in the cache and can be re-used.

Table 194: Payload Cache Entry Management Methods

10.3.2 Applying Data

Data is applied to a cache entry from the payload of an OMM message by using the `apply` method. The decoded `Msg` and an `DecodeIterator` are passed to the `apply` method. The iterator (positioned at the start of the encoded payload data `Msg.encodedDataBody`) will be used to decode the OMM data so that the cache entry data can be set or updated.

Some caching behaviors are controlled by flags in the `Msg`. When a `RefreshMsg` is applied to the cache entry, the following `RefreshMsgFlags` take effect:

- `CLEAR_CACHE`: Cache entry data will be cleared prior to applying this message.
- `DO_NOT_CACHE`: The payload will not be applied to the cache entry.

When an `UpdateMsg` is applied to cache, the following `UpdateMsgFlags` take effect:

- `DO_NOT_CACHE`: The payload data will not be applied to the cache entry.
- `DO_NOT_RIPPLE`: When applying the data, entry rippling is not performed.

The following example demonstrates how to create a payload entry in a cache instance and apply the payload of a `Msg` to the cache entry.

```
/* For simplicity in this code fragment, CHK is assumed to be a macro for error handling (performing
   cleanup and returning from method). */

CacheError cacheError = CacheFactory.createCacheError();
PayloadEntry entryInstance = CacheFactory.createPayloadEntry(cacheInstance, cacheError);
if (entryInstance == null)
{
    System.out.println("Error " + cacheError.errorId() + " creating cache entry: " + cacheError.text());
    CHK(cacheError.errorId());
}

/* Apply buffer containing an encoded Msg to cache entry */
int applyBufferToCache(Channel channel, TransportBuffer buffer, PayloadEntry entryInstance)
{
    /* Perform message decoding. */
    DecodeIterator dIter = CodecFactory.createDecodeIterator();
    dIter.clear();
    dIter.setBufferAndRWFVersion(buffer, channel.majorVersion(), channel.minorVersion());
    Msg msg = CodecFactory.createMsg();
    int ret = msg.decode(dIter);
    if (ret < CodecReturnCodes.SUCCESS)
    {
        System.out.println("Failure decoding message from buffer");
        CHK(ret);
    }

    /* Apply the decoded Msg to cache, with iterator positioned at the start of the payload */
    CacheError cacheError = CacheFactory.createCacheError();
    ret = entryInstance.apply(dIter, msg, cacheError);
    if (ret < CodecReturnCodes.SUCCESS)
    {
        System.out.println("Error " + cacheError.errorId() + " applying data to cache entry: " +
                           cacheError.text());
        CHK(ret);
    }
}
```

```

    CHK(ret);
}

```

Code Example 34: Applying Data to a Payload Cache Entry

10.3.3 Retrieving Data

Data is retrieved from a cache entry as an encoded OMM container by using the `retrieve` method. The application provides the data buffer (via an `EncodeIterator`) where the container will be encoded. The retrieve method supports both encoding scenarios. When using `Msg.encodedDataBody`, the encoded content retrieved from the cache entry can be set on the `Msg` data body. If using `encodeInit` and `encodeComplete` encoding, the cache retrieve method can encode the message payload prior to `encodeComplete`.

There are two options for using the `retrieve` method. For single-part retrieval, the buffer provided by the application must be large enough to hold the entire encoded container. For multi-part retrieval, the application makes a series of calls to `retrieve` to get the OMM container in fragments (e.g., a sequence of maps are retrieved which together contain the entire set of map entries for the container). In this usage, the optional `PayloadCursor` instance is required to maintain the state of the multi-part retrieval. Container types `FieldList` and `ElementList` cannot be fragmented, so the buffer size must be large enough to retrieve the entire container.

The following methods describe data-related operations on a cache entry.

METHOD NAME	DESCRIPTION
dataType	Returns the <code>DataType</code> stored in the cache entry instance. When initially created (or after the entry is cleared), the data type will be <code>UNKNOWN</code> . The data type is defined by the container type of the first refresh message applied to the entry.
apply	Applies the OMM data in the payload of the <code>Msg</code> to the cache entry instance. The first message applied must be a refresh message (class <code>REFRESH</code>).
retrieve	Retrieves data from the cache entry by encoding the OMM container into the buffer provided with the <code>EncodeIterator</code> given by the application. The buffer can be <code>Buffer</code> or <code>TransportBuffer</code> . For single-part retrieval, the <code>PayloadCursor</code> parameter is optional. For details on multi-part retrieval, refer to Section 10.3.3.1.

Table 195: Methods for Applying and Retrieving Cache Entry Data

10.3.3.1 Multi-Part Retrieval

For data types that support fragmentation, the container can be retrieved in multiple parts by calling `retrieve` until the complete container is returned. To support multi-part retrieval, the optional `PayloadCursor` parameter is required when calling `retrieve`. The cursor is used to maintain the position where the next retrieval will resume. The application must check the state of the cursor after each call to `retrieve` to determine when the retrieval is complete. The following methods are needed when using the payload cursor.

METHOD NAME	DESCRIPTION
<code>CacheFactory.createPayloadCursor</code>	Creates a cursor for optional use in the <code>retrieve</code> method (required for multi-part retrieval). Returns the <code>PayloadCursor</code> instance.
<code>destroy</code>	Destroys the cursor instance.

Table 196: Methods for Using the Payload Cursor

METHOD NAME	DESCRIPTION
clear	Clears the state of the cursor instance. Whenever retrieving data from a cache entry, the cursor must be cleared prior to the first call to retrieve . Clearing the cursor also allows it to be reused with a retrieval on a different container.
isComplete	Returns the completion state of a retrieval where the PayloadCursor instance was used. The state must be checked after each call to retrieve to determine whether additional data needs to be encoded for the cache entry container. When the cursor state is complete, the entire container of the cache entry has been retrieved.

Table 196: Methods for Using the Payload Cursor (Continued)

10.3.3.2 Buffer Management

In multi-part usage, the size of the buffer used in the calls to **retrieve** will affect how many fragments are required to retrieve the entire image of the cache entry. The retrieve method will continue to encode OMM entries from the cache container until it runs out of room in the buffer to encode the next entry. To progress during a multi-part retrieval, the buffer size must be at least large enough to encode a single OMM entry from the payload container. For example, if retrieving a map in multiple parts, the buffer must be large enough to encode at least one **MapEntry** on each retrieval.

There are three general outcomes when using the **retrieve** method:

- Full cache container is encoded into the buffer. This can occur with or without the use of the optional **PayloadCursor** instance. If used in this scenario, the cursor state would indicate the retrieval is complete.
- Partial container encoded into the buffer. This is only possible when using the **PayloadCursor** instance for container types that support fragmentation. The application must check the cursor to test whether this is the final part.
- No data encoded into container due to insufficient buffer size. This can occur with or without the use of the optional **PayloadCursor** instance. The application may retrieve again with a larger buffer.

10.3.3.3 Example: Cache Retrieval with Multi-Part Support

The following example illustrates data retrieval from a cache entry, which supports multi-part encoding of a container.

```

/*Code fragment showing use of retrieve for multi-part retrieval.*/
com.refinitiv.eta.transport.Error error = TransportFactory.createError();
TransportBuffer buffer = channel.getBuffer(DEFAULT_BUFFER_SIZE, false, error);

int ret;
CacheError cacheError = CacheFactory.createCacheError();
PayloadCursor cursorInstance = CacheFactory.createPayloadCursor();
cursorInstance.clear();
EncodeIterator eIter = CodecFactory.createEncodeIterator();
while (!cursorInstance.isComplete())
{
    eIter.clear();
    eIter.setBufferAndRWFVersion(buffer, channel.majorVersion(), channel.minorVersion());

    /* entryInstance created outside the scope of this code fragment */
    ret = entryInstance.retrieve(eIter, cursorInstance, cacheError);
    if (ret == CodecReturnCodes.SUCCESS)
        /* buffer is big enough to hold whole container data. Application can used encoded data, e.g. set the
           payload on Msg.encodedDataBody and encode a message to be transmitted. */
    else if (ret == CodecReturnCodes.BUFFER_TOO_SMALL)
        /* Increase buffer size and reallocate buffer. */
    else
        /* Handle terminal error condition. See cacheError.text() for additional information. */
}

cursorInstance.destroy();

```

Code Example 35: Cache Retrieval with Multi-Part Support

Appendix A Value Added Utilities

Value Added Utilities are a collection of common classes used mainly by the Transport API Reactor. Included is a selectable, bidirectional queue that can communicate events between the Reactor and Worker threads. Other Value Added Utilities include a simple queue along with iterable and concurrent versions of it.

The Value Added Utilities are internally leveraged by the Transport API Reactor and cache so applications need not be familiar with their use.

© 2015 - 2023 Refinitiv. All rights reserved.

Republication or redistribution of Refinitiv content, including by framing or similar means, is prohibited without the prior written consent of Refinitiv. 'Refinitiv' and the Refinitiv logo are registered trademarks and trademarks of Refinitiv.

Any third party names or marks are the trademarks or registered trademarks of the relevant third party.

Document ID: ET AJ373UMVAC.230

Date of issue: December 2023

