


Name: Rishita Mote
 TE COMPS / BATCH-B
 UID: 2018130029

CEL 51, DCCN, Monsoon 2020

Lab 7: RIPv2 Router Configuration

Topology Diagram



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	Fa0/0	172.30.1.1	255.255.255.0	N/A
	Fa0/1	172.30.2.1	255.255.255.0	N/A
	S0/0/0	209.165.200.230	255.255.255.252	N/A
R2	Fa0/0	10.1.0.1	255.255.0.0	N/A
	S0/0/0	209.165.200.229	255.255.255.252	N/A
	S0/0/1	209.165.200.233	255.255.255.252	N/A
R3	Fa0/0	172.30.100.1	255.255.255.0	N/A
	S0/0/1	209.165.200.234	255.255.255.252	N/A
	Lo0	172.30.110.1	255.255.255.0	N/A
	Lo1	172.30.200.17	255.255.255.240	N/A

	Lo2	172.30.200.33	255.255.255.240	N/A
PC1	NIC	172.30.2.10	255.255.255.0	172.30.2.1
PC2	NIC	172.30.1.10	255.255.255.0	172.30.1.1
PC3	NIC	10.1.0.10	255.255.0.0	10.1.0.1
PC4	NIC	172.30.100.10	255.255.255.0	172.30.100.1

Learning Objectives

Upon completion of this lab, you will be able to:

- Cable a network according to the Topology Diagram.
- Load provided scripts onto the routers.
- Examine the current status of the network.
- Configure RIPv2 on all routers.
- Examine the automatic summarization of routes.
- Examine routing updates with **debug ip rip**.
- Disable automatic summarization.
- Examine the routing tables.
- Verify network connectivity.
- Document the RIPv2 configuration.

Scenario


The network shown in the Topology Diagram contains a discontiguous network, 172.30.0.0. This network has been subnetted using VLSM. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network, in this case the two serial networks 209.165.200.228/30 and 209.165.200.232/30. This can be an issue when the routing protocol used does not include enough information to distinguish the individual subnets. RIPv2 is a classless routing protocol that can be used to provide subnet mask information in the routing updates. This will allow VLSM subnet information to be propagated throughout the network.

Task 1: Cable, Erase, and Reload the Routers.


Step 1: Cable a network.

Cable a network that is similar to the one in the Topology Diagram.


- Arrange 4 PC's, 4 2960 Switches and 3 1841 routers.




- Connect the switches, pc's and routers using copper straight through cable as shown in the diagram.




- For Serial connection between routers, add WIC-2T cards in each router.




- Connect the routers with serial DCE cable.




- Configuration of PC1:




- Configuration of PC2:




- Configuration of PC3:



- Configuration of PC4:





Step 2: Clear the configuration on each router.

Clear the configuration on each of routers using the **erase startup-config** command and then **reload** the routers. Answer **no** if asked to save changes.

- Clearing configuration of R1:

```
R1
Physical Config CLI Attributes
IOS Command Line Interface
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M),
Version 12.4(15)T1, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#|
```

Ctrl+F6 to exit CLI focus

Top

- Reloading R1:

```

Router#reload
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fc1)
Initializing memory for ECC
..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

 Readonly ROMMON initialized

Self decompressing the image :
#####
##### [OK]
      Restricted Rights Legend

Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Software clause at DFARS sec. 252.227-7013.

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, California 95134-1706

```

Ctrl+F6 to exit CLI focus

Top

- Clearing configuration of R2:

```

Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M),
Version 12.4(15)T1, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
$SYS-7-NV_BLOCK_INIT: Initialized the geometry of nram
Router#

```

Ctrl+F6 to exit CLI focus

Top

- Reloading R2:

```

Router#reload
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fc1)
Initializing memory for ECC
..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

Readonly ROMMON initialized

Self decompressing the image :
#####
##### [OK]
##### Restricted Rights Legend

Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Software clause at DFARS sec. 252.227-7013.

cisco Systems, Inc.
170 West Tasman Drive
San Jose, California 95134-1706

```

Ctrl+F6 to exit CLI focus

Top

- Clearing configuration of R3:

```

Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M),
Version 12.4(15)T1, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#

```

Ctrl+F6 to exit CLI focus

Top

- Reloading R3:

```

Router#reload
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)
Initializing memory for ECC
..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

Readonly ROMMON initialized

Self decompressing the image :
#####
##### [OK]
      Restricted Rights Legend

Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Software clause at DFARS sec. 252.227-7013.

cisco Systems, Inc.
170 West Tasman Drive
San Jose, California 95134-1706

```

Ctrl+F6 to exit CLI focus

Top

Task 2: Load Routers with the Supplied Scripts.

Step 1: Load the following script onto R1.

```

!
hostname R1
!
!
!
interface FastEthernet0/0
ip address 172.30.1.1 255.255.255.0
duplex auto
speed auto
no shutdown
!
interface FastEthernet0/1
ip address 172.30.2.1 255.255.255.0
duplex auto
speed auto


```

```

no shutdown
!
interface Serial0/0/0
ip address 209.165.200.230 255.255.255.252
clock rate 64000
no shutdown
!
router rip
passive-interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.30.0.0
network 209.165.200.0
!
line con 0
line vty 0 4
login
!
end

```

- Assigning hostname as R1:



- Configuring FastEthernet0/0:

```

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#
R1(config)#+Z
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R1(config-if)#
Ctrl+F6 to exit CLI focus

```

- Configuring FastEthernet0/1:

```

R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up


R1(config-if)#exit
R1(config)#interface FastEthernet0/1
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up

Ctrl+F6 to exit CLI focus

```

- Configuring Serial0/0/0:



The screenshot shows the CLI interface for router R1. The tab bar at the top has 'Physical', 'Config', 'CLI' (which is selected), and 'Attributes'. The main window displays the following configuration commands:

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
R1(config-if)#exit
R1(config)#interface FastEthernet0/1
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up


R1(config-if)#exit
R1(config)#interface Serial 0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#

```

At the bottom of the window, there are 'Copy' and 'Paste' buttons, and a checkbox labeled 'Top'.

- Configuration of RIP:



The screenshot shows the CLI interface for router R1. The tab bar at the top has 'Physical', 'Config', 'CLI' (which is selected), and 'Attributes'. The main window displays the following configuration commands:

```
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up


R1(config-if)#exit
R1(config)#interface Serial 0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#
R1(config)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)#passive-interface FastEthernet0/1
R1(config-router)#network 172.30.0.0
R1(config-router)#network 209.165.200.0
R1(config-router)#

```


At the bottom of the window, there are 'Copy' and 'Paste' buttons, and a checkbox labeled 'Top'.

- Running Config:




R1#^Z
R1#show running-config
Building configuration...

Current configuration : 857 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R1
!
!



!
interface FastEthernet0/0
ip address 172.30.1.1 255.255.255.0
duplex auto
speed auto
!
interface FastEthernet0/1
ip address 172.30.2.1 255.255.255.0
duplex auto
speed auto
!
interface Serial0/0/0
ip address 209.165.200.230 255.255.255.252
clock rate 64000
!




Step 2: Load the following script onto R2.

```
hostname R2
!
!
!
interface FastEthernet0/0
ip address 10.1.0.1 255.255.0.0
duplex auto
speed auto
no shutdown
!
interface Serial0/0/0
ip address 209.165.200.229 255.255.255.252
no shutdown
!
interface Serial0/0/1
ip address 209.165.200.233 255.255.255.252
clock rate 64000
no shutdown
!
router rip
passive-interface FastEthernet0/0
```

```
network 10.0.0.0
network 209.165.200.0
!
line con 0
line vty 0 4
login
!
end
```

- Assigning hostname as R2:



- Configuring FastEthernet0/0:

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)#duplex auto
R2(config-if)#speed auto
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
```

Ctrl+F6 to exit CLI focus

Top

- Configuring Serial0/0/0:

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)#duplex auto
R2(config-if)#speed auto
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R2(config-if)#exit
R2(config)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
```

Ctrl+F6 to exit CLI focus

Top

- Configuring Serial0/0/1:

```
R2(config-if)#  
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,  
changed state to up  
  
R2(config-if)#exit  
R2(config)#interface Serial0/0/0  
R2(config-if)#ip address 209.165.200.229 255.255.255.252  
R2(config-if)#no shutdown  
  
R2(config-if)#  
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,  
changed state to up  
  
R2(config-if)#exit  
R2(config)#interface Serial 0/0/1  
R2(config-if)#ip address 209.165.200.233 255.255.255.252  
R2(config-if)#clock rate 64000  
R2(config-if)#no shutdown  
  
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down  
R2(config-if)#[
```

Ctrl+F6 to exit CLI focus

Top

- Configuration of RIP:

```
R2(config-if)#exit  
R2(config)#interface Serial0/0/0  
R2(config-if)#ip address 209.165.200.229 255.255.255.252  
R2(config-if)#no shutdown  
  
R2(config-if)#  
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,  
changed state to up  
  
R2(config-if)#exit  
R2(config)#interface Serial 0/0/1  
R2(config-if)#ip address 209.165.200.233 255.255.255.252  
R2(config-if)#clock rate 64000  
R2(config-if)#no shutdown  
  
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down  
R2(config-if)#exit  
R2(config)#router rip  
R2(config-router)#passive-interface FastEthernet0/0  
R2(config-router)#network 10.0.0.0  
R2(config-router)#network 209.165.200.0  
R2(config-router)#[
```

Ctrl+F6 to exit CLI focus

Top

- Running Config:

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R2#show running-config
Building configuration...

Current configuration : 803 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R2
!
!
!
!
!
!
!
no ip cef
no ipv6 cef
!
```

R2

Physical Config **CLI** Attributes


IOS Command Line Interface

```
!
!
interface FastEthernet0/0
ip address 10.1.0.1 255.255.0.0
duplex auto
speed auto
!
interface FastEthernet0/1
no ip address
duplex auto
speed auto
shutdown
!
interface Serial0/0/0
ip address 209.165.200.229 255.255.255.252
!
interface Serial0/0/1
ip address 209.165.200.233 255.255.255.252
clock rate 64000
!
interface Vlan1
no ip address
shutdown
!
--More--
```

Ctrl+F6 to exit CLI focus

Top

Copy Paste




Step 3: Load the following script onto R3.

```
hostname R3
!
!
!
interface FastEthernet0/0
ip address 172.30.100.1 255.255.255.0
duplex auto
speed auto
no shutdown
!
interface Serial0/0/1
ip address 209.165.200.234 255.255.255.252
no shutdown
!
interface Loopback0
ip address 172.30.110.1 255.255.255.0
!
interface Loopback1
```

```
ip address 172.30.200.17 255.255.255.240
!
interface Loopback2
ip address 172.30.200.33 255.255.255.240
!
router rip
passive-interface FastEthernet0/0
network 172.30.0.0
network 209.165.200.0
!
line con 0
line vty 0 4
login
!
end
```

- Assigning hostname as R3:



- Configuration of FastEthernet0/0:

```
Router>
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)#duplex auto
R3(config-if)#speed auto
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
```

Ctrl+F6 to exit CLI focus

Top

- Configuration of Serial0/0/1:

```
Router>
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)#duplex auto
R3(config-if)#speed auto
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up


R3(config-if)#exit
R3(config)#interface Serial0/0/1
R3(config-if)#ip address 209.165.200.234 255.255.255.252
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
```

Ctrl+F6 to exit CLI focus

Top

- Configuration of Loopback0:



The screenshot shows the Cisco IOS CLI interface for router R3. The window title is "R3". The tabs at the top are "Physical", "Config", "CLI" (which is selected), and "Attributes". The main area is titled "IOS Command Line Interface". The command history is as follows:

```

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R3(config-if)#exit
R3(config)#interface Serial0/0/1
R3(config-if)#ip address 209.165.200.234 255.255.255.252
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up

R3(config-if)#exit
R3(config)#interface Loopback0

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0,
changed state to up

R3(config-if)#ip address 172.30.110.1 255.255.255.0
R3(config-if)#

```

At the bottom of the CLI window, there are buttons for "Copy" and "Paste", and a checkbox labeled "Top".

- Configuration of Loopback1:



The screenshot shows the Cisco IOS CLI interface for router R3. The window title is "R3". The tabs at the top are "Physical", "Config", "CLI" (which is selected), and "Attributes". The main area is titled "IOS Command Line Interface". The command history is as follows:

```

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up

R3(config-if)#exit
R3(config)#interface Loopback0

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0,
changed state to up

R3(config-if)#ip address 172.30.110.1 255.255.255.0
R3(config-if)#exit
R3(config)#interface Loopback1

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1,
changed state to up

R3(config-if)#ip address 172.30.200.17 255.255.255.240
R3(config-if)#

```

At the bottom of the CLI window, there are buttons for "Copy" and "Paste", and a checkbox labeled "Top".

- Configuration of Loopback2:

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
R3(config-if)#ip address 172.30.110.1 255.255.255.0
R3(config-if)#exit
R3(config)#interface Loopback1

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1, changed state to up

R3(config-if)#ip address 172.30.200.17 255.255.255.240
R3(config-if)#exit
R3(config)#interface Loopback2

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2, changed state to up

R3(config-if)#ip address 172.30.200.33 255.255.255.240
R3(config-if)#

```

Ctrl+F6 to exit CLI focus

Top

- Configuration of RIP:

```
R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1, changed state to up

R3(config-if)#ip address 172.30.200.17 255.255.255.240
R3(config-if)#exit
R3(config)#interface Loopback2

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2, changed state to up

R3(config-if)#ip address 172.30.200.33 255.255.255.240
R3(config-if)#
R3(config-if)#exit
R3(config)#router rip
R3(config-router)#passive-interface FastEthernet0/0
R3(config-router)#network 172.30.0.0
R3(config-router)#network 209.165.200.0
R3(config-router)#

```

Ctrl+F6 to exit CLI focus

Top

- Running Configuration:

The image displays two windows of the Cisco IOS Command Line Interface (CLI) for a device named R3. Both windows show the output of the command `show running-config`.

Top Window Output:

```
R3#show running-config
Building configuration...
!
Current configuration : 983 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R3
!
!
!
!
!
!
no ip cef
no ipv6 cef
!
!--More--
```

Bottom Window Output:

```
!
!
!
!
interface Loopback0
ip address 172.30.110.1 255.255.255.0
!
interface Loopback1
ip address 172.30.200.17 255.255.255.240
!
interface Loopback2
ip address 172.30.200.33 255.255.255.240
!
interface FastEthernet0/0
ip address 172.30.100.1 255.255.255.0
duplex auto
speed auto
!
interface FastEthernet0/1
no ip address
duplex auto
speed auto
shutdown
--More-- |
```

R3

Physical Config **CLI** Attributes


IOS Command Line Interface

```
!
interface Serial0/0/1
ip address 209.165.200.234 255.255.255.252
!
interface Vlan1
no ip address
shutdown
!
router rip
passive-interface FastEthernet0/0
network 172.30.0.0
network 209.165.200.0
!
ip classless
!
ip flow-export version 9
!
!
!
!
!
!
!
line console 0
!
```

Ctrl+F6 to exit CLI focus

Top

Final Topology:




Task 3: Examine the Current Status of the Network.

Step 1: Verify that both serial links are up.

The two serial links can quickly be verified using the **show ip interface brief** command on R2.

R2#**show ip interface brief**



A screenshot of a terminal window showing the output of the 'show ip interface brief' command on a Cisco router. The output lists various interfaces (FastEthernet0/0, FastEthernet0/1, Serial0/0/0, Serial0/0/1, Vlan1) with their IP addresses, status (OK? Method Status), and protocol status (Protocol up/down).

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	10.1.0.1	YES	manual	up	up
FastEthernet0/1	unassigned	YES	NVRAM	administratively down	down
Serial0/0/0	209.165.200.229	YES	manual	up	up
Serial0/0/1	209.165.200.233	YES	manual	up	up
Vlan1	unassigned	YES	NVRAM	administratively down	down

Ctrl+F6 to exit CLI focus

Top

Step 2: Check the connectivity from R2 to the hosts on the R1 and R3 LANs.

Note: For the 1841 router, you will need to disable IP CEF to obtain the correct output from the **ping** command. Although a discussion of IP CEF is beyond the scope of this course, you may disable IP CEF by using the following command in global configuration mode:

R2(config)#**no ip cef**

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R2>enable
R2#show ip interface brief
Interface          IP-Address      OK? Method Status
Protocol
FastEthernet0/0      10.1.0.1       YES manual up
up
FastEthernet0/1      unassigned     YES NVRAM
administratively down down
Serial0/0/0          209.165.200.229 YES manual up
up
Serial0/0/1          209.165.200.233 YES manual up
up
Vlan1               unassigned     YES NVRAM
administratively down down
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#no ip cef
R2(config)#[
```

Ctrl+F6 to exit CLI focus Copy Paste

R1

Physical Config **CLI** Attributes

IOS Command Line Interface


```
Press RETURN to get started.

R1>enable
R1#configure terminal
^
* Invalid input detected at '^' marker.

R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#no ip cef
R1(config)#[
```

Ctrl+F6 to exit CLI focus Copy Paste

Top



- Ping PC1 from R2:

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
administratively down down
Serial0/0/0      209.165.200.229 YES manual up
up
Serial0/0/1      209.165.200.233 YES manual up
up
Vlan1           unassigned      YES NVRAM
administratively down down
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#no ip cef
R2(config)#^Z
R2#
*SYS-5-CONFIG_I: Configured from console by console
R2#ping 172.30.2.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.2.10, timeout is 2
seconds:
.U!.!
Success rate is 40 percent (2/5), round-trip min/avg/max =
1/4/5 ms
R2#
```

Ctrl+F6 to exit CLI focus

Top

From the R2 router, how many ICMP messages are successful when pinging PC1?

Ans: **2 ICMP messages are successful.**

- Ping PC4 from R2:

The screenshot shows a Windows application window titled "R2". The window has a tab bar with "Physical", "Config", "CLI" (which is underlined in blue), and "Attributes". Below the tabs is a title bar "IOS Command Line Interface". The main area contains the following CLI session output:

```
Z.  
R2(config)#no ip cef  
R2(config)#^Z  
R2#  
%SYS-5-CONFIG_I: Configured from console by console  
  
R2#ping 172.30.2.10  
  
Type escape sequence to abort.  
Sending 5, 100-byte ICMP Echos to 172.30.2.10, timeout is 2  
seconds:  
.U!.!  
Success rate is 40 percent (2/5), round-trip min/avg/max =  
1/4/5 ms  
  
R2#ping 172.30.100.10  
  
Type escape sequence to abort.  
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is  
2 seconds:  
.U!.!  
Success rate is 40 percent (2/5), round-trip min/avg/max =  
1/2/3 ms  
  
R2#
```


At the bottom left of the window, it says "Ctrl+F6 to exit CLI focus". On the right side, there are "Copy" and "Paste" buttons. At the very bottom left is a checkbox labeled "Top".

From the R2 router, how many ICMP messages are successful when pinging PC4?

Ans: 2 ICMP messages are successful.

Step 3: Check the connectivity between the PCs.

- Ping PC2 from PC1:



The screenshot shows a Windows Command Prompt window titled "PC1". The window has a menu bar with tabs: Physical, Config, Desktop (which is selected), Programming, and Attributes. Below the menu is a title bar with "Command Prompt" and a close button. The main area of the window displays the output of a ping command. The output shows two sets of ping results. The first set is for IP address 172.30.1.10, where one packet timed out and three were received. The second set is for IP address 172.30.1.10, where all four packets were received successfully. The command prompt prompt is visible at the bottom.

```
Packet Tracer PC Command Line 1.0
C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:

Request timed out.
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127
Reply from 172.30.1.10: bytes=32 time=1ms TTL=127

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:

Reply from 172.30.1.10: bytes=32 time<1ms TTL=127

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```


From the PC1, is it possible to ping PC2?

=> Yes.

What is the success rate?

=> 100%

- Ping PC3 from PC1:



```
PC1

Physical Config Desktop Programming Attributes

Command Prompt X

Reply from 172.30.1.10: bytes=32 time<1ms TTL=127
Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:

Reply from 172.30.1.10: bytes=32 time<1ms TTL=127

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Request timed out.
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Request timed out.
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 1ms, Average = 1ms

C:\>
```

Top


From the PC1, is it possible to ping PC3?

=> Yes

What is the success rate?

=> 50%

- Ping PC4 from PC1:



The screenshot shows a Windows Command Prompt window titled "PC1". The window has a menu bar with tabs: Physical, Config, Desktop, Programming, and Attributes. The "Desktop" tab is selected. Below the menu is a title bar labeled "Command Prompt" with a close button "X". The main area of the window displays the output of a ping command. The output shows two successful pings to 10.1.0.10 and four failed pings to 172.30.100.10, resulting in 100% loss.

```
Reply from 10.1.0.10: bytes=32 time=1ms TTL=128
Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 1ms, Average = 1ms

C:\>
C:\>ping 172.30.100.10

Pinging 172.30.100.10 with 32 bytes of data:

Reply from 172.30.2.1: Destination host unreachable.

Ping statistics for 172.30.100.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>
```

From the PC1, is it possible to ping PC4?

=> No

What is the success rate?

=> 0%

- Ping PC2 from PC4:

```

Packet Tracer PC Command Line 1.0
C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:

Reply from 172.30.100.1: Destination host unreachable.

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>

```

From the PC4, is it possible to ping PC2? => **No**

What is the success rate? => **0%**

- Ping PC3 from PC4:

```

Packet Tracer PC Command Line 1.0
C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:

Reply from 172.30.100.1: Destination host unreachable.

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=2ms TTL=126
Request timed out.
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Request timed out.

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 2ms, Average = 1ms
C:\>

```

From the PC4, is it possible to ping PC3? => **Yes.**

What is the success rate? => **50%**

Step 4: View the routing table on R2.

Both the R1 and R3 are advertising routes to the 172.30.0.0/16 network; therefore, there are two entries for this network in the R2 routing table. The R2 routing table only shows the major classful network address of 172.30.0.0—it does not show any of the subnets for this network that are used on the LANs attached to R1 and R3. Because the routing metric is the same for both entries, the router alternates the routes that are used when forwarding packets that are destined for the 172.30.0.0/16 network.

R2#show ip route

```
R2>enable
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
      * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route

Gateway of last resort is not set

      10.0.0.0/16 is subnetted, 1 subnets
C        10.1.0.0 is directly connected, FastEthernet0/0
R        172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:16, Serial0/0/0
                  [120/1] via 209.165.200.234, 00:00:24, Serial0/0/1
          209.165.200.0/30 is subnetted, 2 subnets
C          209.165.200.228 is directly connected, Serial0/0/0
C          209.165.200.232 is directly connected, Serial0/0/1

R2#
```

Ctrl+F6 to exit CLI focus


Top

Step 5: Examine the routing table on the R1 router.

Both R1 and R3 are configured with interfaces on a discontiguous network, 172.30.0.0. The 172.30.0.0 subnets are physically and logically divided by at

least one other classful or major network—in this case, the two serial networks 209.165.200.228/30 and 209.165.200.232/30. Classful routing protocols like RIPv1 summarize networks at major network boundaries. Both R1 and R3 will be summarizing 172.30.0.0/24 subnets to 172.30.0.0/16. Because the route to 172.30.0.0/16 is directly connected, and because R1 does not have any specific routes for the 172.30.0.0 subnets on R3, packets destined for the R3 LANs will not be forwarded properly.

R1#show ip route



```
R1>enable
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
      * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:17, Serial0/0/0
      172.30.0.0/24 is subnetted, 2 subnets
C        172.30.1.0 is directly connected, FastEthernet0/0
C        172.30.2.0 is directly connected, FastEthernet0/1
      209.165.200.0/30 is subnetted, 2 subnets
C          209.165.200.228 is directly connected, Serial0/0/0
R          209.165.200.232 [120/1] via 209.165.200.229, 00:00:17, Serial0/0/0

R1#
```

Ctrl+F6 to exit CLI focus

Top

Step 6: Examine the routing table on the R3 router.

R3 only shows its own subnets for 172.30.0.0 network: 172.30.100/24, 172.30.110/24, 172.30.200.16/28, and 172.30.200.32/28. R3 does not have any routes for the 172.30.0.0 subnets on R1.

R3#**show ip route**

The screenshot shows the Cisco Network Assistant interface with the title bar "R3". Below it is a tab bar with "Physical", "Config", "CLI" (which is selected), and "Attributes". The main window is titled "IOS Command Line Interface". The output of the "show ip route" command is displayed:

```
R3>enable
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
      * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:22, Serial0/0/1
      172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks
C      172.30.100.0/24 is directly connected, FastEthernet0/0
C      172.30.110.0/24 is directly connected, Loopback0
C      172.30.200.16/28 is directly connected, Loopback1
C      172.30.200.32/28 is directly connected, Loopback2
      209.165.200.0/30 is subnetted, 2 subnets
R      209.165.200.228 [120/1] via 209.165.200.233, 00:00:22, Serial0/0/1
C      209.165.200.232 is directly connected, Serial0/0/1

R3#
```

At the bottom of the interface, there are buttons for "Copy" and "Paste". Below the main window, there is a "Top" button.

Step 7: Examine the RIPv1 packets that are being received by R2.

Use the **debug ip rip** command to display RIP routing updates.

R2 is receiving the route 172.30.0.0, with 1 hop, from both R1 and R3. Because these are equal cost metrics, both routes are added to the R2 routing table. Because RIPv1 is a classful routing protocol, no subnet mask information is sent in the update.

R2#debug ip rip

```
R2#debug ip rip
RIP protocol debugging is on
R2#RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
RIP: received v1 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
RIP: received v1 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
```

```
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
RIP: received v1 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
RIP: received v1 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
```

R2 is sending only the routes for the 10.0.0.0 LAN and the two serial connections to R1 and R3. R1 and R3 are not receiving any information about the 172.30.0.0 subnet routes.

When you are finished, turn off the debugging.

R2#undebbug all

```
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
RIP: received v1 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
undebbug all
All possible debugging has been turned off
R2#
```

Task 4: Configure RIP Version 2.

Step 1: Use the version 2 command to enable RIP version 2 on each of the routers.

```
R2(config)#router rip
R2(config-router)#version 2
```

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
RIP: received v1 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0 in 1 hops
RIP: received v1 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.232 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    network 10.0.0.0 metric 1
    network 209.165.200.228 metric 1
undebbug all
All possible debugging has been turned off
R2#
R2#
R2#
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#router rip
R2(config-router)#version 2
R2(config-router)#

```

Ctrl+F6 to exit CLI focus Top Copy Paste

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
shutdown
!
router rip
version 2
passive-interface FastEthernet0/0
network 10.0.0.0
network 209.165.200.0
!
ip classless
!
ip flow-export version 9
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
--More--

```

Ctrl+F6 to exit CLI focus Top Copy Paste

R1(config)#router rip
R1(config-router)#version 2

The screenshot shows a Cisco IOS Command Line Interface window titled "R1". The window has tabs for "Physical", "Config", "CLI", and "Attributes", with "CLI" being the active tab. The main area is labeled "IOS Command Line Interface". It displays the following configuration commands:

```
R1>enable
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#router rip
R1(config-router)#version 2
R1(config-router)#[
```

At the bottom of the window, there are buttons for "Copy" and "Paste", and a checkbox labeled "Top".

The screenshot shows a Cisco IOS Command Line Interface window titled "R1". The window has tabs for "Physical", "Config", "CLI", and "Attributes", with "CLI" being the active tab. The main area is labeled "IOS Command Line Interface". It displays a full configuration dump, starting with "shutdown" and including "router rip", "ip classless", and "line" configurations. A "More" prompt is visible at the bottom.

```
shutdown
!
router rip
version 2
passive-interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.30.0.0
network 209.165.200.0
!
ip classless
!
ip flow-export version 9
!
!
!
!
!
line con 0
!
line aux 0
!
--More-- |
```

At the bottom of the window, there are buttons for "Copy" and "Paste", and a checkbox labeled "Top".

```
R3(config)#router rip  
R3(config-router)#version 2
```

The screenshot shows a Windows-style application window titled "R3". The window has tabs at the top: "Physical", "Config", "CLI" (which is selected), and "Attributes". Below the tabs is a title bar "IOS Command Line Interface". The main area contains the following text:

```
Press RETURN to get started.  
  
R3>  
R3>enable  
R3#configure terminal  
Enter configuration commands, one per line. End with CNTL/Z.  
R3(config)#router rip  
R3(config-router)#version 2  
R3(config-router)#
```

At the bottom left, there is a note: "Ctrl+F6 to exit CLI focus". On the right side, there are "Copy" and "Paste" buttons. At the very bottom, there is a checkbox labeled "Top".

This screenshot shows the same "R3" CLI window, but the configuration text is much longer and more detailed, indicating a full configuration rather than just the RIP section shown above.

```
router rip  
version 2  
passive-interface FastEthernet0/0  
network 172.30.0.0  
network 209.165.200.0  
!  
ip classless  
!  
ip flow-export version 9  
!
```


RIPv2 messages include the subnet mask in a field in the routing updates. This allows subnets and their masks to be included in the routing updates. However, by default RIPv2 summarizes networks at major network

boundaries, just like RIPv1, except that the subnet mask is included in the update.

Step 2: Verify that RIPv2 is running on the routers.

The **debug ip rip**, **show ip protocols**, and **show run** commands can all be used to confirm that RIPv2 is running. The output of the **show ip protocols** command for R1 is shown below.

R1# **show ip protocols**



```
R1#
R1#
R1#show ip protocols
Routing Protocol is "rip"
  Sending updates every 30 seconds, next due in 12 seconds
  Invalid after 180 seconds, hold down 180, flushed after 240
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
  Redistributing: rip
  Default version control: send version 2, receive 2
    Interface      Send   Recv   Triggered RIP  Key-chain
    Serial0/0/0        2       2
  Automatic network summarization is in effect
  Maximum path: 4
  Routing for Networks:
    172.30.0.0
    209.165.200.0
  Passive Interface(s):
    FastEthernet0/0
    FastEthernet0/1
  Routing Information Sources:
    Gateway          Distance      Last Update
    209.165.200.229         120      00:00:09
  Distance: (default is 120)
R1#
```

Ctrl+F6 to exit CLI focus

Top

Task 5: Examine the Automatic Summarization of Routes.

The LANs connected to R1 and R3 are still composed of discontiguous networks. R2 still shows two equal cost paths to the 172.30.0.0/16 network in the routing table. R2 still shows only the major classful network address of 172.30.0.0 and does not show any of the subnets for this network.

R2#**show ip route**

R2#
R2#
R2#
R2#
R2#
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets
C 10.1.0.0 is directly connected, FastEthernet0/0
R 172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:00, Serial0/0/0
[120/1] via 209.165.200.234, 00:00:12, Serial0/0/1
209.165.200.0/30 is subnetted, 2 subnets
C 209.165.200.228 is directly connected, Serial0/0/0
C 209.165.200.232 is directly connected, Serial0/0/1

R2#

Ctrl+F6 to exit CLI focus

Top

R1 still shows only its own subnets for the 172.30.0.0 network. R1 still does not have any routes for the 172.30.0.0 subnets on R3.

R1#show ip route

R1

Physical Config **CLI** Attributes

IOS Command Line Interface

Gateway	Distance	Last Update
209.165.200.229	120	00:00:09

Distance: (default is 120)
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

R 10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:10, Serial0/0/0
172.30.0.0/16 is variably subnetted, 3 subnets, 2 masks
R 172.30.0.0/16 is possibly down, routing via 209.165.200.229,
Serial0/0/0
C 172.30.1.0/24 is directly connected, FastEthernet0/0
C 172.30.2.0/24 is directly connected, FastEthernet0/1
209.165.200.0/30 is subnetted, 2 subnets
C 209.165.200.228 is directly connected, Serial0/0/0
R 209.165.200.232 [120/1] via 209.165.200.229, 00:00:10, Serial0/0/0

R1#

Ctrl+F6 to exit CLI focus

Top

R3 still only shows its own subnets for the 172.30.0.0 network. R3 still does not have any routes for the 172.30.0.0 subnets on R1.

R3#show ip route



- □ ×

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R3#
R3#
R3#
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
      * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:05, Serial0/0/1
      172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks
C      172.30.100.0/24 is directly connected, FastEthernet0/0
C      172.30.110.0/24 is directly connected, Loopback0
C      172.30.200.16/28 is directly connected, Loopback1
C      172.30.200.32/28 is directly connected, Loopback2
      209.165.200.0/30 is subnetted, 2 subnets
R      209.165.200.228 [120/1] via 209.165.200.233, 00:00:05, Serial0/0/1
C      209.165.200.232 is directly connected, Serial0/0/1
```


R3#

Ctrl+F6 to exit CLI focus

Top

Use the output of the **debug ip rip** command to answer the following questions:

- For R3:



The screenshot shows a Cisco IOS Command Line Interface (CLI) window titled "R3". The window has tabs for "Physical", "Config", "CLI" (which is selected), and "Attributes". The main area displays the output of the "debug ip rip" command. The output shows RIP protocol debugging is on, and it lists several "v2 update" messages being sent via different interfaces (Loopback0, Loopback1, Loopback2, and Serial0/0/1) to various IP addresses with specific metrics and tags.

```
R3#debug ip rip
RIP protocol debugging is on
R3#RIP: sending v2 update to 224.0.0.9 via Loopback0 (172.30.110.1)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
  209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback1 (172.30.200.17)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
  209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback2 (172.30.200.33)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
  209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.234)
```

Ctrl+F6 to exit CLI focus

Top

R3

Physical Config **CLI** Attributes

IOS Command Line Interface

```
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.234)
RIP: build update entries
  172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.233 on Serial0/0/1
  10.0.0.0/8 via 0.0.0.0 in 1 hops
  209.165.200.228/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Loopback0 (172.30.110.1)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
  209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback1 (172.30.200.17)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback2 (172.30.200.33)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
```

Ctrl+F6 to exit CLI focus

Top

R3

Physical Config **CLI** Attributes

IOS Command Line Interface

```
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.234)
RIP: build update entries
  172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.233 on Serial0/0/1
  10.0.0.0/8 via 0.0.0.0 in 1 hops
  209.165.200.228/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Loopback0 (172.30.110.1)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
  209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback1 (172.30.200.17)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
  209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback2 (172.30.200.33)
RIP: build update entries
  10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
```

Ctrl+F6 to exit CLI focus

Top

- For R2:

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R2>enable
R2#debug ip rip
RIP protocol debugging is on
R2#RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.229)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1
(209.165.200.233)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.229)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1
(209.165.200.233)
RIP: build update entries
```

Ctrl+F6 to exit CLI focus

Top

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1
(209.165.200.233)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.229)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1
(209.165.200.233)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0/16 via 0.0.0.0 in 1 hops
```

Ctrl+F6 to exit CLI focus

Top

R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1
(209.165.200.233)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.229)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
    209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
undeRIP: received v2 update from 209.165.200.234 on Serial0/0/1
    172.30.0.0/16 via 0.0.0.0 in 1 h
R2#undebug all
All possible debugging has been turned off
R2#
```

Ctrl+F6 to exit CLI focus

Top

- For R1:

R1

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R1>enable
R1#debug ip rip
RIP protocol debugging is on
R1#RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.0.0.0/8 via 0.0.0.0 in 1 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.0.0.0/8 via 0.0.0.0 in 1 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.0.0.0/8 via 0.0.0.0 in 1 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
```

Ctrl+F6 to exit CLI focus

Top

R1

Physical Config **CLI** Attributes

IOS Command Line Interface

```
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.0.0.0/8 via 0.0.0.0 in 1 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.0.0.0/8 via 0.0.0.0 in 1 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.0.0.0/8 via 0.0.0.0 in 1 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
```

Ctrl+F6 to exit CLI focus

Top

What entries are included in the RIP updates sent out from R3?

=>

1. **10.0.0.0/8**
2. **172.30.100.0/24**
3. **172.30.110.0/24**
4. **172.30.200.16/24**
5. **209.165.200.0/24**

On R2, what routes are in the RIP updates that are received from R3?

Ans: **172.30.0.0/16**

R3 is not sending any of the 172.30.0.0 subnets—only the summarized route of 172.30.0.0/16, including the subnet mask. This is why R2 and R1 are not seeing the 172.30.0.0 subnets on R3.

Task 6: Disable Automatic Summarization.

The **no auto-summary** command is used to turn off automatic summarization in RIPv2. Disable auto summarization on all routers. The routers will no longer summarize routes at major network boundaries.

```
R2(config)#router rip  
R2(config-router)#no auto-summary
```

```
R2#  
R2>  
R2>  
R2#configure terminal  
Enter configuration commands, one per line. End with CNTL/Z.  
R2(config)#router rip  
R2(config-router)#no auto-summary  
R2(config-router)#
```

```
shutdown
!
router rip
version 2
passive-interface FastEthernet0/0
network 10.0.0.0
network 209.165.200.0
no auto-summary
!
ip classless
!
ip flow-export version 9
!
!
!
line con 0
!
line aux 0
!
--More-- |
```

Ctrl+F6 to exit CLI focus Copy Paste

Top

R1(config)#router rip
R1(config-router)#no auto-summary

```
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
  10.0.0.0/8 via 0.0.0.0 in 1 hops
  209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
  172.30.0.0/16 via 0.0.0.0, metric 1, tag 0
undebug a;
^
% Invalid input detected at '^' marker.

R1#RIP: received v2 update from 209.165.200.229 on Serial0/0/0
  10.0.0.0/8 via 0.0.0.0 in 1 hops
  209.165.200.232/30 via 0.0.0.0 in 1 hops
undebug all
All possible debugging has been turned off
R1#
R1#
R1#
R1#
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#router rip
R1(config-router)#no auto-summary
R1(config-router) #
```

Ctrl+F6 to exit CLI focus Copy Paste

Top

R3(config)#router rip
R3(config-router)#no auto-summary

```

Press RETURN to get started.

R3>enable
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#router rip
R3(config-router)#no auto-summary
R3(config-router)#

```

Ctrl+F6 to exit CLI focus Copy Paste

Top

The **show ip route** and **ping** commands can be used to verify that automatic summarization is off.

Task 7: Examine the Routing Tables.

The LANs connected to R1 and R3 should now be included in all three routing tables.

R2#**show ip route**

```

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets
C    10.1.0.0 is directly connected, FastEthernet0/0
172.30.0.0/16 is variably subnetted, 7 subnets, 3 masks
R      172.30.0.0/16 is possibly down, routing via 209.165.200.230, Serial0/0/0
          is possibly down, routing via 209.165.200.234, Serial0/0/1
R      172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:24, Serial0/0/0
R      172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:24, Serial0/0/0
R      172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:01, Serial0/0/1
R      172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:01, Serial0/0/1
R      172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:01, Serial0/0/1
R      172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:01, Serial0/0/1
209.165.200.0/30 is subnetted, 2 subnets
C      209.165.200.228 is directly connected, Serial0/0/0
C      209.165.200.232 is directly connected, Serial0/0/1


R2#

```

Ctrl+F6 to exit CLI focus Copy Paste

Top

R1#show ip route




```
R1
Physical Config CLI Attributes
IOS Command Line Interface
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter
      area
      * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/16 is subnetted, 1 subnets
R    10.1.0.0 [120/1] via 209.165.200.229, 00:00:27, Serial0/0/0
  172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C      172.30.1.0/24 is directly connected, FastEthernet0/0
C      172.30.2.0/24 is directly connected, FastEthernet0/1
R      172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:27, Serial0/0/0
R      172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:27, Serial0/0/0
R      172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:27, Serial0/0/0
R      172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:27, Serial0/0/0
  209.165.200.0/30 is subnetted, 2 subnets
C      209.165.200.228 is directly connected, Serial0/0/0
R      209.165.200.232 [120/1] via 209.165.200.229, 00:00:27, Serial0/0/0

R1#
Ctrl+F6 to exit CLI focus           Copy   Paste
 Top
```

R3#show ip route



```
R3
Physical Config CLI Attributes
IOS Command Line Interface
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/16 is subnetted, 1 subnets
R    10.1.0.0 [120/1] via 209.165.200.233, 00:00:05, Serial0/0/1
  172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R    172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:05, Serial0/0/1
R    172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:05, Serial0/0/1
C    172.30.100.0/24 is directly connected, FastEthernet0/0
C    172.30.110.0/24 is directly connected, Loopback0
C    172.30.200.16/28 is directly connected, Loopback1
C    172.30.200.32/28 is directly connected, Loopback2
  209.165.200.0/30 is subnetted, 2 subnets
R    209.165.200.228 [120/1] via 209.165.200.233, 00:00:05,
Serial0/0/1
C    209.165.200.232 is directly connected, Serial0/0/1

R3#
Ctrl+F6 to exit CLI focus           Copy   Paste
 Top
```

Use the output of the **debug ip rip** command to answer the following questions:

- For R1:

The screenshot shows a Cisco IOS CLI interface titled "R1". The "CLI" tab is selected. The output of the "debug ip rip" command is displayed in a scrollable text area. The output shows RIP protocol debugging is on, and various RIP events such as sending and receiving v2 updates, building update entries, and route changes. The text area ends with "RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.230)". Below the text area are "Copy" and "Paste" buttons, and a "Ctrl+F6 to exit CLI focus" instruction. At the bottom left is a "Top" button.

```
R1#debug ip rip
RIP protocol debugging is on
R1#RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.230)
RIP: build update entries
    172.30.1.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.2.0/24 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.1.0.0/16 via 0.0.0.0 in 1 hops
    172.30.100.0/24 via 0.0.0.0 in 2 hops
    172.30.110.0/24 via 0.0.0.0 in 2 hops
    172.30.200.16/28 via 0.0.0.0 in 2 hops
    172.30.200.32/28 via 0.0.0.0 in 2 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.230)
RIP: build update entries
    172.30.1.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.2.0/24 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.1.0.0/16 via 0.0.0.0 in 1 hops
    172.30.100.0/24 via 0.0.0.0 in 2 hops
    172.30.110.0/24 via 0.0.0.0 in 2 hops
    172.30.200.16/28 via 0.0.0.0 in 2 hops
    172.30.200.32/28 via 0.0.0.0 in 2 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.230)
```

What entries are included in the RIP updates sent out from R1?

Ans:

1. **172.30.1.0/24**
2. **172.30.2.0/24**

- On R2:

```

R2>enable
R2#debug ip rip
RIP protocol debugging is on
R2#RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
  10.1.0.0/16 via 0.0.0.0, metric 1, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 2, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 2, tag 0
  172.30.200.16/28 via 0.0.0.0, metric 2, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 2, tag 0
  209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
  10.1.0.0/16 via 0.0.0.0, metric 1, tag 0
  172.30.1.0/24 via 0.0.0.0, metric 2, tag 0
  172.30.2.0/24 via 0.0.0.0, metric 2, tag 0
  209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.234 on Serial0/0/1
  172.30.100.0/24 via 0.0.0.0 in 1 hops
  172.30.110.0/24 via 0.0.0.0 in 1 hops
  172.30.200.16/28 via 0.0.0.0 in 1 hops
  172.30.200.32/28 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
  172.30.1.0/24 via 0.0.0.0 in 1 hops
  172.30.2.0/24 via 0.0.0.0 in 1 hops
Ctrl+F6 to exit CLI focus

```

```

172.30.200.32/28 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
  172.30.1.0/24 via 0.0.0.0 in 1 hops
  172.30.2.0/24 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
  10.1.0.0/16 via 0.0.0.0, metric 1, tag 0
  172.30.100.0/24 via 0.0.0.0, metric 2, tag 0
  172.30.110.0/24 via 0.0.0.0, metric 2, tag 0
  172.30.200.16/28 via 0.0.0.0, metric 2, tag 0
  172.30.200.32/28 via 0.0.0.0, metric 2, tag 0
  209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
  10.1.0.0/16 via 0.0.0.0, metric 1, tag 0
  172.30.1.0/24 via 0.0.0.0, metric 2, tag 0
  172.30.2.0/24 via 0.0.0.0, metric 2, tag 0
  209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
RIP: received v2 update from 209.165.200.234 on Serial0/0/1
  172.30.100.0/24 via 0.0.0.0 in 1 hops
  172.30.110.0/24 via 0.0.0.0 in 1 hops
  172.30.200.16/28 via 0.0.0.0 in 1 hops
  172.30.200.32/28 via 0.0.0.0 in 1 hops
RIP: received v2 update from 209.165.200.230 on Serial0/0/0
  172.30.1.0/24 via 0.0.0.0 in 1 hops
Ctrl+F6 to exit CLI focus

```

On R2, what routes are in the RIP updates that are received from R1?

Ans:

- 1. 172.30.1.0/24**
- 2. 172.30.2.0/24**

Are the subnet masks now included in the routing updates?

Ans: Yes.

Task 8: Verify Network Connectivity.

Step 1: Check connectivity between R2 router and PCs.

- Ping PC1 from R2.

```
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.229)
RIP: build update entries
    10.1.0.0/16 via 0.0.0.0, metric 1, tag 0
    172.30.100.0/24 via 0.0.0.0, metric 2, tag 0
    172.30.110.0/24 via 0.0.0.0, metric 2, tag 0
    172.30.200.16/28 via 0.0.0.0, metric 2, tag 0
    172.30.200.32/28 via 0.0.0.0, metric 2, tag 0
    209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.233)
RIP: build update entries
    10.1.0.0/16 via 0.0.0.0, metric 1, tag 0
    172.30.1.0/24 via 0.0.0.0, metric 2, tag 0
    172.30.2.0/24 via 0.0.0.0, metric 2, tag 0
    209.165.200.228/30 via 0.0.0.0, metric 1, tag 0
undebug all
All possible debugging has been turned off
R2#
R2#ping 172.30.2.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.2.10, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/3/8 ms
R2#
```

From R2, how many ICMP messages are successful when pinging PC1?

Ans: 5 ICMP messages are successful.

- Ping PC4 from R2

```
R2#ping 172.30.100.10
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/3/14 ms
R2#
```

Ctrl+F6 to exit CLI focus **Copy** **Paste**


Top

From R2, how many ICMP messages are successful when pinging PC4?

Ans: **5 ICMP messages are successful.**

Step 2: Check the connectivity between the PCs.

- Ping PC2 from PC1:



```
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>ping 172.30.100.10

Pinging 172.30.100.10 with 32 bytes of data:
Reply from 172.30.2.1: Destination host unreachable.

Ping statistics for 172.30.100.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>ping 172.30.1.10


Pinging 172.30.1.10 with 32 bytes of data:
Reply from 172.30.1.10: bytes=32 time=1ms TTL=127
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
C:\>
```

From PC1, is it possible to ping PC2? => Yes

What is the success rate? 100%

- Ping PC3 from PC1:



The screenshot shows a Windows Command Prompt window titled "PC1". The window has tabs at the top: Physical, Config, Desktop (which is selected), Programming, and Attributes. The main area displays the following command-line session:

```
Command Prompt
Reply from 172.30.2.1: Destination host unreachable.
Reply from 172.30.2.1: Destination host unreachable.
Reply from 172.30.2.1: Destination host unreachable.

Ping statistics for 172.30.100.10:
  Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127

Ping statistics for 172.30.1.10:
  Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
  Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:
Reply from 10.1.0.10: bytes=32 time=2ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=2ms TTL=126

Ping statistics for 10.1.0.10:
  Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
  Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>
```

From PC1, is it possible to ping PC3? => Yes

What is the success rate? => 100%

- Ping PC4 from PC1:

```
PC1
Physical Config Desktop Programming Attributes
Command Prompt X
Reply from 172.30.1.10: bytes=32 time<1ms TTL=127
Ping statistics for 172.30.1.10:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
C:\>ping 10.1.0.10
Pinging 10.1.0.10 with 32 bytes of data:
Reply from 10.1.0.10: bytes=32 time=2ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=2ms TTL=126
Ping statistics for 10.1.0.10:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 2ms, Average = 1ms
C:\>ping 172.30.100.10
Pinging 172.30.100.10 with 32 bytes of data:
Reply from 172.30.100.10: bytes=32 time=3ms TTL=125
Reply from 172.30.100.10: bytes=32 time=13ms TTL=125
Reply from 172.30.100.10: bytes=32 time=2ms TTL=125
Reply from 172.30.100.10: bytes=32 time=4ms TTL=125
Ping statistics for 172.30.100.10:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 2ms, Maximum = 13ms, Average = 5ms
C:\>
```

From PC1, is it possible to ping PC4? => Yes

What is the success rate? => 100%


- Ping PC2 from PC4:

```
PC4
Physical Config Desktop Programming Attributes
Command Prompt X
C:\>
C:\>ping 172.30.1.10
Pinging 172.30.1.10 with 32 bytes of data:
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
Reply from 172.30.1.10: bytes=32 time=10ms TTL=125
Ping statistics for 172.30.1.10:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 2ms, Maximum = 10ms, Average = 4ms
C:\>
```

From PC4, is it possible to ping PC2? => Yes

What is the success rate? => 100%

- Ping PC3 from PC4:



The screenshot shows a Windows Command Prompt window titled "PC4". The window has tabs at the top: Physical, Config, Desktop (which is selected), Programming, and Attributes. The main area is a "Command Prompt" window with the following text output:

```
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:

Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
Reply from 172.30.1.10: bytes=32 time=10ms TTL=125

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 10ms, Average = 4ms

C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=1ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 1ms, Average = 1ms

C:\>
```

At the bottom left of the window, there is a checkbox labeled "Top".

From PC4, is it possible to ping PC3? => Yes

What is the success rate? 100%

Task 9: Documentation

On each router, capture the following command output to a text (.txt) file and save for future reference.

- **show running-config**
- **show ip route**
- **show ip interface brief**
- **show ip protocols**

If you need to review the procedures for capturing command output, refer to Lab 1.5.1.

Txt file:

Show Running-config

R1:

```
R1#show running-config
```

```
Building configuration...
```

```
Current configuration : 885 bytes
```

```
!
```

```
version 12.4
```

```
no service timestamps log datetime msec
```

```
no service timestamps debug datetime msec
```

```
no service password-encryption
```

```
!
```

```
hostname R1
```

```
!
```

```
!
```

```
!
```

```
!
```

```
!
```

```
!
```

```
!
```

```
no ip cef  
no ipv6 cef
```

```
!  
!  
!  
!  
!  
!  
!  
!  
!  
!  
!
```

```
spanning-tree mode pvst
```

```
!  
!  
!  
!  
!  
!
```

```
interface FastEthernet0/0  
ip address 172.30.1.1 255.255.255.0  
duplex auto  
speed auto
```

```
!
```

```
interface FastEthernet0/1  
ip address 172.30.2.1 255.255.255.0  
duplex auto  
speed auto
```

```
!  
interface Serial0/0/0  
ip address 209.165.200.230 255.255.255.252  
clock rate 64000  
!  
interface Serial0/0/1  
no ip address  
clock rate 2000000  
shutdown  
!  
interface Vlan1  
no ip address  
shutdown  
!  
router rip  
version 2  
passive-interface FastEthernet0/0  
passive-interface FastEthernet0/1  
network 172.30.0.0  
network 209.165.200.0  
no auto-summary  
!  
ip classless  
!  
ip flow-export version 9  
!  
!  
!
```

```
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
login
!
!
!
```

end

R2:

R2#show running-config

Building configuration...

Current configuration : 831 bytes

```
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R2
!
!
```

!

!

!

!

!

no ip cef

no ipv6 cef

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

spanning-tree mode pvst

!

!

!

!

!

!

!

!

!

!

interface FastEthernet0/0

ip address 10.1.0.1 255.255.0.0

duplex auto

speed auto

```
!  
interface FastEthernet0/1  
no ip address  
duplex auto  
speed auto  
shutdown  
!  
interface Serial0/0/0  
ip address 209.165.200.229 255.255.255.252  
!  
interface Serial0/0/1  
ip address 209.165.200.233 255.255.255.252  
clock rate 64000  
!  
interface Vlan1  
no ip address  
shutdown  
!  
router rip  
version 2  
passive-interface FastEthernet0/0  
network 10.0.0.0  
network 209.165.200.0  
no auto-summary  
!  
ip classless  
!  
ip flow-export version 9  
!  
!
```

```
!
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
login
!
!
!
end
```

R3:

```
R3#show running-config
Building configuration...

Current configuration : 1011 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R3
```

!

!

!

!

!

!

!

no ip cef

no ipv6 cef

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

spanning-tree mode pvst

!

!

!

!

!

!

!

interface Loopback0

```
ip address 172.30.110.1 255.255.255.0
!
interface Loopback1
ip address 172.30.200.17 255.255.255.240
!
interface Loopback2
ip address 172.30.200.33 255.255.255.240
!
interface FastEthernet0/0
ip address 172.30.100.1 255.255.255.0
duplex auto
speed auto
!
interface FastEthernet0/1
no ip address
duplex auto
speed auto
shutdown
!
interface Serial0/0/0
no ip address
clock rate 2000000
shutdown
!
interface Serial0/0/1
ip address 209.165.200.234 255.255.255.252
!
interface Vlan1
no ip address
shutdown
```

```
!  
router rip  
version 2  
passive-interface FastEthernet0/0  
network 172.30.0.0  
network 209.165.200.0  
no auto-summary  
!  
ip classless  
!  
ip flow-export version 9  
!  
!  
!  
!  
!  
!  
!  
!  
!  
line con 0  
!  
line aux 0  
!  
line vty 0 4  
login  
!  
!  
!  
end
```

Show ip route:

R1:

R1#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets

R 10.1.0.0 [120/1] via 209.165.200.229, 00:00:30, Serial0/0/0

172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks

C 172.30.1.0/24 is directly connected, FastEthernet0/0

C 172.30.2.0/24 is directly connected, FastEthernet0/1

R 172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:30, Serial0/0/0

R 172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:30, Serial0/0/0

R 172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:30, Serial0/0/0

R 172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:30, Serial0/0/0

209.165.200.0/30 is subnetted, 2 subnets

C 209.165.200.228 is directly connected, Serial0/0/0

R 209.165.200.232 [120/1] via 209.165.200.229, 00:00:30, Serial0/0/0

R2:

R2#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets

C 10.1.0.0 is directly connected, FastEthernet0/0

172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks

R 172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:10, Serial0/0/0

R 172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:10, Serial0/0/0

R 172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:18, Serial0/0/1

R 172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:18, Serial0/0/1

R 172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:18, Serial0/0/1

R 172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:18, Serial0/0/1

209.165.200.0/30 is subnetted, 2 subnets

C 209.165.200.228 is directly connected, Serial0/0/0

C 209.165.200.232 is directly connected, Serial0/0/1

R2#

R3:

R3#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets

R 10.1.0.0 [120/1] via 209.165.200.233, 00:00:12, Serial0/0/1

172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks

R 172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:12, Serial0/0/1

R 172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:12, Serial0/0/1

C 172.30.100.0/24 is directly connected, FastEthernet0/0

C 172.30.110.0/24 is directly connected, Loopback0

C 172.30.200.16/28 is directly connected, Loopback1

C 172.30.200.32/28 is directly connected, Loopback2

209.165.200.0/30 is subnetted, 2 subnets

R 209.165.200.228 [120/1] via 209.165.200.233, 00:00:12, Serial0/0/1

C 209.165.200.232 is directly connected, Serial0/0/1

R3#

Show ip interface brief:

R1:

R1#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	172.30.1.1	YES	manual	up	
FastEthernet0/1	172.30.2.1	YES	manual	up	
Serial0/0/0	209.165.200.230	YES	manual	up	
Serial0/0/1	unassigned	YES	NVRAM	administratively down	down
Vlan1	unassigned	YES	NVRAM	administratively down	down

R1#

R2:

R2#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	10.1.0.1	YES	manual	up	
FastEthernet0/1	unassigned	YES	NVRAM	administratively down	down
Serial0/0/0	209.165.200.229	YES	manual	up	
Serial0/0/1	209.165.200.233	YES	manual	up	
Vlan1	unassigned	YES	NVRAM	administratively down	down

R2#

R3:

R3#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
-----------	------------	-----	--------	--------	----------

```
FastEthernet0/0    172.30.100.1  YES manual up          up
FastEthernet0/1    unassigned   YES NVRAM administratively down down
Serial0/0/0        unassigned   YES NVRAM administratively down down
Serial0/0/1        209.165.200.234 YES manual up          up
Loopback0          172.30.110.1  YES manual up          up
Loopback1          172.30.200.17  YES manual up          up
Loopback2          172.30.200.33  YES manual up          up
Vlan1              unassigned   YES NVRAM administratively down down
R3#
```

Show ip protocols:

R1:

R1#show ip protocols

Routing Protocol is "rip"

Sending updates every 30 seconds, next due in 10 seconds

Invalid after 180 seconds, hold down 180, flushed after 240

Outgoing update filter list for all interfaces is not set

Incoming update filter list for all interfaces is not set

Redistributing: rip

Default version control: send version 2, receive 2

Interface	Send	Recv	Triggered RIP	Key-chain
-----------	------	------	---------------	-----------

Serial0/0/0	2	2		
-------------	---	---	--	--

Automatic network summarization is not in effect

Maximum path: 4

Routing for Networks:

172.30.0.0

209.165.200.0

Passive Interface(s):

FastEthernet0/0

FastEthernet0/1

Routing Information Sources:

Gateway	Distance	Last Update
209.165.200.229	120	00:00:03

Distance: (default is 120)

R1#

R2:

R2#show ip protocols

Routing Protocol is "rip"

Sending updates every 30 seconds, next due in 14 seconds

Invalid after 180 seconds, hold down 180, flushed after 240

Outgoing update filter list for all interfaces is not set

Incoming update filter list for all interfaces is not set

Redistributing: rip

Default version control: send version 2, receive 2

Interface	Send	Recv	Triggered RIP	Key-chain
-----------	------	------	---------------	-----------

Serial0/0/0	2	2		
-------------	---	---	--	--

Serial0/0/1	2	2		
-------------	---	---	--	--

Automatic network summarization is not in effect

Maximum path: 4

Routing for Networks:

10.0.0.0

209.165.200.0

Passive Interface(s):

FastEthernet0/0

Routing Information Sources:

Gateway	Distance	Last Update
209.165.200.230	120	00:00:27
209.165.200.234	120	00:00:10

Distance: (default is 120)

R2#

R3:

R3#show ip protocols

Routing Protocol is "rip"

Sending updates every 30 seconds, next due in 10 seconds

Invalid after 180 seconds, hold down 180, flushed after 240

Outgoing update filter list for all interfaces is not set

Incoming update filter list for all interfaces is not set

Redistributing: rip

Default version control: send version 2, receive 2

Interface	Send	Recv	Triggered RIP	Key-chain
-----------	------	------	---------------	-----------

Loopback0	2	2		
-----------	---	---	--	--

Loopback1	2	2		
-----------	---	---	--	--

Loopback2	2	2		
-----------	---	---	--	--

Serial0/0/1	2	2		
-------------	---	---	--	--

Automatic network summarization is not in effect

Maximum path: 4

Routing for Networks:

172.30.0.0

209.165.200.0

Passive Interface(s):

FastEthernet0/0

Routing Information Sources:

Gateway	Distance	Last Update
---------	----------	-------------


209.165.200.233	120	00:00:21
-----------------	-----	----------

Distance: (default is 120)

Task 10: Clean Up

Erase the configurations and reload the routers. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.

- Erase configuration for R1 and reload:



R1

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R1#erase startup-config
Erasing the nvram filesystem will remove all configuration files! Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
R1#reload
System configuration has been modified. Save? [yes/no]:no
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fc1)
Initializing memory for ECC
...
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

 Readonly ROMMON initialized

Self decompressing the image :
#####
[OK]
 Restricted Rights Legend


Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Programs clause at FAR sec. 52.232-14, unless otherwise specified in
the contract, order, or agreement.
```

Ctrl+F6 to exit CLI focus

Top

Copy Paste

- Erase configuration for R2 and reload:



R2

Physical Config **CLI** Attributes

IOS Command Line Interface

```
R2#erase startup-config
Erasing the nvram filesystem will remove all configuration files! Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
R2#reload
System configuration has been modified. Save? [yes/no]:no
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fc1)
Initializing memory for ECC
...
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

 Readonly ROMMON initialized

Self decompressing the image :
#####
[OK]
 Restricted Rights Legend

Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Programs clause at FAR sec. 52.232-14, unless otherwise specified in
the contract, order, or agreement.
```

Ctrl+F6 to exit CLI focus

Top

Copy Paste

- Erase configuration for R3 and reload:

```
R3#erase startup-config
Erasing the nvram filesystem will remove all configuration files! Continue? [confirm]
[OK]
Erase of nvram: complete
*SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
R3#reload
System configuration has been modified. Save? [yes/no]:no
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fc1)
Initializing memory for ECC
...
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

 Readonly ROMMON initialized

 Self decompressing the image :
#####
##### [OK]
 Restricted Rights Legend

Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Software License Agreement.
```

Ctrl+F6 to exit CLI focus

Top

Copy Paste

Conclusion:

1. In this experiment, I learned about the routing protocols
2. I implemented RIPv2 on the given topology and documented the results.