MIDIcvt Developer's Reference Manual 0.3

Generated by Doxygen 1.8.9.1

Thu Aug 20 2015 06:24:59

ii CONTENTS

Contents

1	midi	cvt		1
	1.1	Introdu	uction	1
2	The	libmidit	filex Library	2
	2.1	Introdu	uction to the MIDI File Library Module	2
3	The	libmidi	pp Library	3
	3.1	Introdu	uction to the MIDIcvt Library Module	3
4	Lice	nses, M	MIDIcvt Projects.	3
	4.1	Licens	e Terms for the midicvt project	3
	4.2	XPC A	Application License	3
	4.3	XPC L	ibrary License	4
	4.4	XPC D	Occumentation License	4
	4.5	XPC A	Affero License	4
	4.6	XPC L	icense Summary	5
5	Todo	o List		5
6	Data	Struct	ure Index	5
	6.1	Data S	Structures	5
7	File	Index		6
	7.1	File Lis	st	6
8	Data	Struct	ure Documentation	7
	8.1	midipp	o::csvarray Class Reference	7
		8.1.1	Detailed Description	9
		8.1.2	Member Typedef Documentation	10
		8.1.3	Constructor & Destructor Documentation	10
		8.1.4	Member Function Documentation	10
		8.1.5	Field Documentation	12
	8.2	midipp	c:initree Class Reference	12
		8.2.1	Detailed Description	15
		8.2.2	Member Typedef Documentation	15
		8.2.3	Constructor & Destructor Documentation	16
		8.2.4	Member Function Documentation	16
		8.2.5	Field Documentation	21
	8.3	midipp	o::midimapper Class Reference	21
		8.3.1	Detailed Description	24
		8.3.2	Constructor & Destructor Documentation	24

		8.3.3	Member Function Documentation	26
		8.3.4	Field Documentation	30
	8.4	midipp	::stringmap < VALUETYPE > Class Template Reference	32
		8.4.1	Detailed Description	34
		8.4.2	Member Typedef Documentation	34
		8.4.3	Constructor & Destructor Documentation	34
		8.4.4	Member Function Documentation	35
		8.4.5	Field Documentation	38
9	Eilo I	Doouma	entation	38
•	9.1		y.cpp File Reference	38
	0.1	9.1.1	Detailed Description	38
		9.1.2	Macro Definition Documentation	39
		9.1.3	Function Documentation	39
	9.2		y.hpp File Reference	39
	3.2	9.2.1	Detailed Description	40
		9.2.2	Function Documentation	41
	9.3	-	es.hpp File Reference	41
	0.0	9.3.1	Detailed Description	43
	9.4		cpp File Reference	43
		9.4.1	Detailed Description	44
		9.4.2	Function Documentation	45
	9.5	initree.	hpp File Reference	45
		9.5.1	Detailed Description	46
		9.5.2	Function Documentation	46
	9.6	iniwritir	ng.cpp File Reference	47
		9.6.1	Detailed Description	48
	9.7	iniwritir	ng.hpp File Reference	48
		9.7.1	Detailed Description	49
	9.8	mainpa	ge-reference.dox File Reference	49
		9.8.1	Detailed Description	49
	9.9	midi_fu	inctions.dox File Reference	49
		9.9.1	Detailed Description	49
	9.10	midicvt	_base.c File Reference	49
		9.10.1	Detailed Description	52
		9.10.2	Macro Definition Documentation	54
		9.10.3	Function Documentation	54
	9.11	midicvt	_base.h File Reference	69
		9.11.1	Detailed Description	71
		9.11.2	Function Documentation	71

iv CONTENTS

9.12	midicvt_globals.c File Reference	72
	9.12.1 Detailed Description	73
	9.12.2 Function Documentation	73
	9.12.3 Variable Documentation	74
9.13	midicvt_globals.h File Reference	74
	9.13.1 Detailed Description	76
	9.13.2 Macro Definition Documentation	76
	9.13.3 Function Documentation	76
	9.13.4 Variable Documentation	76
9.14	midicvt_helpers.c File Reference	76
	9.14.1 Detailed Description	78
	9.14.2 Macro Definition Documentation	78
	9.14.3 Function Documentation	78
	9.14.4 Variable Documentation	80
9.15	midicvt_helpers.h File Reference	81
	9.15.1 Detailed Description	82
	9.15.2 Function Documentation	82
9.16	midicvt_license.dox File Reference	84
	9.16.1 Detailed Description	84
9.17	midicvt_m2m.c File Reference	84
	9.17.1 Detailed Description	86
	9.17.2 Function Documentation	86
9.18	midicvt_m2m.h File Reference	97
	9.18.1 Detailed Description	98
	9.18.2 Function Documentation	98
9.19	midicvt_macros.h File Reference	101
	9.19.1 Detailed Description	
	9.19.2 Macro Definition Documentation	103
9.20		104
	9.20.1 Detailed Description	104
	9.20.2 Function Documentation	105
9.21	midicvtpp_main.cpp File Reference	105
	9.21.1 Detailed Description	106
	9.21.2 Function Documentation	107
	9.21.3 Variable Documentation	108
9.22		109
	·	111
		112
		122
9.23	midifilex.h File Reference	123

1 midicvt 1

	9.23.1 Detailed Description	125
	9.23.2 Macro Definition Documentation	125
	9.23.3 Function Documentation	125
9.24	midimapper.cpp File Reference	129
	9.24.1 Detailed Description	130
	9.24.2 Function Documentation	131
	9.24.3 Variable Documentation	133
9.25	midimapper.hpp File Reference	133
	9.25.1 Detailed Description	134
	9.25.2 Function Documentation	135
9.26	midipp_functions.dox File Reference	137
	9.26.1 Detailed Description	137
9.27	stringmap.cpp File Reference	137
	9.27.1 Detailed Description	137
	9.27.2 Function Documentation	138
9.28	stringmap.hpp File Reference	138
	9.28.1 Detailed Description	139
	9.28.2 Function Documentation	140
9.29	t2m_no_flex.c File Reference	140
	9.29.1 Detailed Description	141
	9.29.2 Function Documentation	142
	9.29.3 Variable Documentation	145
9.30	t2mf.h File Reference	146
	9.30.1 Detailed Description	147
	9.30.2 Macro Definition Documentation	147
	9.30.3 Variable Documentation	147
9.31	VERSION.h File Reference	148
	9.31.1 Detailed Description	148
Index		149

1 midicvt

Author(s) Chris Ahlstrom 2015-08-14

1.1 Introduction

MIDIcvt is a minor cleanup, refactoring, and documentation of the related midi2text and midicomp projects.

The purpose of these projects is to convert MIDI to and from a human-readable, machine-parsed text format, for easy modifications to MIDI files using standard tools.

In addition to the *midicvt* C program, this project includes a refactored version of *libmidifile* called *libmidifilex*, a new library called *libmidipp*, and a C++ program called *midicvtpp* that includes the functionality of *midicvt* and adds some

canned MIDI-to-MIDI transformations to save the user the writing of some scripts.

The current document describes the functions, classes, modules, and other entities used in this project.

The following changes were made to the *midicomp* project to make it easier to understand and modify:

- The ancient Kernighan and Ritchie conventions for C function parameters were used for the parameters of the libmidifile functions. We changed these conventions to modern C.
- The comments about functions and values were increased in depth, and were converted to use Doxygen/

 JavaDocs conventions, so that a reference manual could be generated.
- We regrouped the global variables into semi-private modules, and added accessor functions to those that needed to be used by callers outside of the library.
- We moved code around and added modules so that the code was better organized, and the main() function much simpler.
- · We rename the library to libmidifilex to avoid conflicts with the old library.
- We added a minor reporting facility so that the existing callbacks could dump information.
- We added an additional set of C callbacks that transformed MIDI to MIDI. (These callbacks tend to fix issue in the input MIDI file, as well.)
- We added a C++ class with static callbacks that can be used to remap notes and patches, extract or reject a given MIDI channel, and make other stock changes to a MIDI file.
- We added a C++ program that can perform some MIDI-to-MIDI conversions without the need for scripting.

2 The libmidifilex Library

2.1 Introduction to the MIDI File Library Module

This library (*libmidifilex*) is based on the work of Tim Thompson (tjt@blink.att.com), and updates by Michael Czeiszperger (mike@pan.com) and Piet van Oostrum (piet@cs.ruu.nl). Chris Ahlstrom (ahlstromcj@gmail.com) made further updates for readability, documentation, coding conventions, and further bug fixes.

The many global variables were moved into their own modules, and C accessor functions were written for many of them, so that the main routines of programs based on this library did not need the declaration of these variables. This made it a lot easier to figure out the functionality of the code and add new functionality to it.

The following modules are included:

- midicvt_base Provides public functions for initializing the private data used in MIDI-to-text and text-to-MIDI conversions.
- midicvt globals Provides access to private options via public pointers or setter/getter (accessor) functions.
- midicvt_helpers Provides accessor functions for version information, help, setting up any input or output files, and parsing the command line.
- midicvt_m2m Exposes new libmidifilex callback functions for usage in the midicvtpp C++ application.
- midicvt_macros Defines common macros for MIDI processing, plus some "info-print" macros. Also included are macros to simulate the "bool" type and its values in C++.
- midicvt_filex Provides slightly enhanced versions of the support functions and callback function of the older library. Also defines the macros defined by the original version of the library.
- t2mf These modules specify the text-to-MIDI conversion of the original midicomp program. They are defined
 using lex (flex) to generate C files that can parse the data. For convenience, a prebuilt module called t2m_←
 no_flex is provided to avoid having to install flex in order to build this project.

3 The libmidipp Library

3.1 Introduction to the MIDIcvt Library Module

This library (libmidipp) is merely a convenience library for the C++ application midicvtpp.

It provides local versions of the following classes:

- midipp:csvarray This class provides a data structure that is a list of items created from a comma-separatedvalue (CSV) file.
- midipp::stringmap This class holds a lookup-table that maps values to string names. It is a fairly reusable class; the midipp version is included here to avoid dependencies on other project libraries we maintain. We want the MIDI programs and libraries to stand on their own, for the convenient of other developers.
- midipp::initree This class holds data for "sections" of midipp::stringmap<std::string> items that represent name/value pairs grouped into sections. This class is created using the data from a special initialization (INI) file.
- midipp::midimapper This class provides data structures to remap drum notes, program (patch) values, and other items. This class is created using the data from a midipp::initree data structure.

4 Licenses, MIDIcvt Projects.

Author(s) Chris Ahlstrom 2015-08-14

4.1 License Terms for the midicvt project.

Wherever the tag \$XPC_SUITE_GPL_LICENSE\$ appears, substitute the appropriate license text, depending on whether the project is a library, application, documentation, or server software. We're not going to include paragraphs of licensing information in every module; you are responsible for coming here to read the licensing information.

These licenses apply to each sub-project and file artifact in the **XPC** library suite.

Wherever the term **XPC** is encountered in this project, it refers to the **XPC Development Suite** on **SourceForge.** ← **net**, which is also called the **XPC Library Suite**, and may be provided at other sites.

4.2 XPC Application License

The XPC application license is the GNU GPLv3.

Copyright (C) 2008-2014 by Chris Ahlstrom

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU GPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/gpl-3.0.txt
```

4.3 XPC Library License

The XPC library license is the GNU LGPLv3.

Copyright (C) 2008-2014 by Chris Ahlstrom

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Lesser Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU LGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/lgpl-3.0.txt
```

4.4 XPC Documentation License

The XPC documentation license is the GNU FDLv1.3.

Copyright (C) 2014-2014 by Chris Ahlstrom

This documentation is free documentation; you can redistribute it and/or modify it under the terms of the GNU Free Documentation License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Free Documentation License along with this documentation; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU FDL version 1.3 license can also be found here:

```
http://www.gnu.org/licenses/fdl.txt
```

4.5 XPC Affero License

The XPC "Affero" license is the GNU AGPLv3.

Copyright (C) 2008-2014 by Chris Ahlstrom

This server software is free server software; you can redistribute it and/or modify it under the terms of the GNU Affero General Public License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Affero General Public License along with this server software; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU AGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/agpl-3.0.txt
```

At the present time, no XPC project uses the "Affero" license.

4.6 XPC License Summary

Include one of these licenses in your Doxygen documentation with one of the following Doxygen tags:

```
\ref midicvt_suite_license_subproject
\ref midicvt_suite_license_application
\ref midicvt_suite_license_library
\ref midicvt_suite_license_documentation
\ref midicvt_suite_license_affero
```

For more information on navigating GNU licensing, see this page:

```
http://www.gnu.org/licenses/
```

Copies of these licenses (and some logos) are provided in the licenses directory of the main project (or you can search for them at *gnu.org*).

5 Todo List

globalScope > Global m2m_mseq (short int num)

Need to figure out the portable format of the sequence number bytes.

Class midipp::stringmap < VALUETYPE >

Consider implementing lookup by integer index; right now, iterators suffice;

It would be nice to be able to superimpose a numeric order on the container, somehow.

globalScope> Global read32bit (void)

We need to use an actual 32-bit return type for 64-bit systems.

• Do we need to make the temp variables volatile; can the compiler reorder them?

globalScope > Global write32bit (unsigned long data)

Provide the proper 32-bit data types needed to do this more portably.

6 Data Structure Index

6.1 Data Structures

Here are the data structures with brief descriptions:

midipp::csvarray

Assist in parsing a file that has lines of comma-separated values

??

	This class provides a way to read and represent an INI file as a kind of tree structure that can be navigate to look up information	??
	midipp::midimapper This class provides for some basic remappings to be done to MIDI files, using the old and new facilities of libmidifilex	??
	midipp::stringmap < VALUETYPE > Provides an std::map wrapper geared towards using std::string as a key	??
7	File Index	
7.1	File List	
Нe	ere is a list of all documented files with brief descriptions:	
	csvarray.cpp Primitive, but useful, CSV-file input parser	??
	csvarray.hpp Library libmidipp	??
	ininames.hpp Provides some free functions to write INI files, given a midipp::csvarray object	??
	initree.cpp Primitive INI-file input parser derived from the XPC library	??
	initree.hpp Provides a "tree" that represents an INI file with named and unnamed sections, and name/value pairs	??
	iniwriting.cpp Provides some free functions to write INI files, given a midipp::csvarray object	??
	iniwriting.hpp Provides some free functions to write INI files, given a midipp::csvarray object	??
	lex.yy.c	??
	midicvt_base.c This module provides functions for basic MIDI/text conversions	??
	midicvt_base.h This module provides functions for a basic MIDI/text conversion application	??
	midicvt_globals.c This module provides a place to collect all the global variables used, and functions to set them	??
	midicvt_globals.h This module provides global variables and accessor functions for the midicvt portion of libmidifilex	??
	midicvt_helpers.c This module provides the help text for midicvt	??
	midicvt_helpers.h This module declares the help and version functions for midicvt	??

midicvt_m2m.c This module provides functions for basic MIDI-to-MIDI conversions	??
midicvt_m2m.h This module provides functions for a basic MIDI-to-MIDI conversion application	??
midicvt_macros.h This module provides macros for generating simple messages, MIDI parameters, and more	??
midicvt_main.c This module creates the midicvt program for translating between MIDI files and text files	??
midicvtpp_main.cpp This module creates the midicvtpp program for translating between MIDI files and text files, and doing some basic remapping operations	??
midifilex.c This module provides functions for handling the reading and writing of MIDI files	??
midifilex.h This module provides functions for libmidifilex	??
midimapper.cpp This module provides functions for advanced MIDI/text conversions	??
midimapper.hpp This module provides functions for advanced MIDI/text conversions	??
stringmap.cpp Library libmidipp	??
stringmap.hpp Library libmidipp	??
t2m_no_flex.c This file is to be used instead of the dynamically generated t2mflex.c if there is no flex program installed or if the installed flex is old [e.g 2.5.35 as opposed to 2.5.39 (!)]	?1
t2mf.h This module provides global variables for the text-to-MIDI conversion portion of libmidifilex	??
VERSION.h This module provides simpler version information for the libmidifilex library	??

8 Data Structure Documentation

8.1 midipp::csvarray Class Reference

The csvarray class assist in parsing a file that has lines of comma-separated values.

#include <csvarray.hpp>

Collaboration diagram for midipp::csvarray:

midipp::csvarray - m_separator - m_source_file - m_name - m_csv_lines - m_minimum_length - m_maximum_length - m_is_valid + csvarray() + csvarray() + csvarray() + operator=() + ~csvarray() + is_valid() + rows() + source_file() + name() + name() + size() + empty() + min_count() + max_count() # readfile() # is_comment() # clear()

Public Types

typedef std::vector< std::string > Fields

Provides a handy type for the data structure that the csvarray class stores in a vector.

typedef std::vector< Fields > Rows

Provides a type that holds a vector of Field elements.

Public Member Functions

• csvarray ()

Creates an unnamed and empty csvarray.

csvarray (const std::string &name, const std::string &filespec, char separator= ',')

Creates an named, but empty, csvarray.

• csvarray (const csvarray &source)

Copy constructor for csvarray.

• csvarray & operator= (const csvarray &source)

Principal assignment operator for csvarray.

virtual ∼csvarray ()

Destructor

• bool is_valid () const

'Getter' function for member m_is_valid;

· const Rows & rows () const

'Getter' function for member m csv lines

• const std::string & source_file () const

'Getter' function for member m_source_file

• const std::string & name () const

'Getter' function for member m_name

void name (const std::string &n)

'Setter' function for member m_name

• size_t size () const

Accessor m_csv_lines.size()

· bool empty () const

Accessor m_csv_lines.empty()

int min_count () const

'Getter' function for member m_minimum_length

• int max_count () const

'Getter' function for member m maximum length

Protected Member Functions

• bool readfile (const std::string &filespec)

Opens a file, and tries to construct an csvarray object, and a number of section objects, in it.

• bool is comment (char c)

Checks for a comment character.

• void clear ()

Allows the container to be emptied of Section objects.

Private Attributes

· char m_separator

Provides the value for the separator.

• std::string m_source_file

Provides the file-name of the file from which this data was instantiated.

std::string m_name

Provides the name of this object, for future reference.

Rows m_csv_lines

Provides a section container.

int m_minimum_length

Indicates the minimum number of fields found in a row.

int m_maximum_length

Indicates the maximum number of fields found in a row.

· bool m_is_valid

Indicates if construction succeeded in all respects.

8.1.1 Detailed Description

The csvarray class assist in parsing a file that has lines of comma-separated values.

It creates a vector of vectors out of this file. The main vector contains one element for each usable line in the file. Each element is itself a vector of strings. A record is kept of the number of elements in each vector. Generally, that number should be the same for every line in the file, but this is not required.

Definition at line 37 of file csvarray.hpp.

8.1.2 Member Typedef Documentation

8.1.2.1 typedef std::vector<std::string> midipp::csvarray::Fields

Provides a handy type for the data structure that the csvarray class stores in a vector.

Each string in this vector is called a "field".

Definition at line 48 of file csvarray.hpp.

8.1.3 Constructor & Destructor Documentation

```
8.1.3.1 midipp::csvarray::csvarray ( )
```

Creates an unnamed and empty csvarray.

The name can be added later with a call to name(), and sections can be added with the insert() function.

Definition at line 44 of file csvarray.cpp.

8.1.3.2 midipp::csvarray::csvarray (const std::string & name, const std::string & filespec, char separator = ' , ')

Creates an named, but empty, csvarray.

The name can be added or modified later with a call to name(), and sections can be added with the std::vector ← ::push_back() function.

If a file-name is given, the file is read to fill in the lines. unnamed section. If it isn't used, the overhead isn't significant.

Parameters

name	Provides the name of the csvarray object.
filespec	Provides the optional full path file-specification for the file to be opened and read to create all
	of the lines specified in that file.
separator	Provides the separator character that demarcates fields. The default value of this parameter
	is the comma.

Definition at line 78 of file csvarray.cpp.

8.1.3.3 midipp::csvarray::csvarray (const csvarray & source)

Copy constructor for csvarray.

Parameters

source	Provides the original object to be copied.
--------	--

Definition at line 102 of file csvarray.cpp.

8.1.3.4 virtual midipp::csvarray::~csvarray() [inline],[virtual]

Destructor

Provided as a virtual destructor so that we can derive from this class.

Definition at line 127 of file csvarray.hpp.

8.1.4 Member Function Documentation

8.1.4.1 bool midipp::csvarray::empty () const [inline]

Accessor m_csv_lines.empty()

Returns

Returns true if the container is empty.

Definition at line 196 of file csvarray.hpp.

8.1.4.2 bool midipp::csvarray::is_comment(char c) [inline], [protected]

Checks for a comment character.

Returns

Returns 'true' if the character is in the set #;

Definition at line 230 of file csvarray.hpp.

8.1.4.3 csvarray & midipp::csvarray::operator= (const csvarray & source)

Principal assignment operator for csvarray.

Parameters

source	Provides the original object to be assigned.
--------	--

Definition at line 122 of file csvarray.cpp.

8.1.4.4 bool midipp::csvarray::readfile (const std::string & filespec) [protected]

Opens a file, and tries to construct an csvarray object, and a number of section objects, in it.

This function reads a file line by line.

- · Blank lines are skipped.
- Lines that start with ";", "#", "!", """, or """ are considered to be blank lines.
- Lines that start with "[" are potentially section-names; if not, then they are considered errors and processing fails.
- Lines that start with alphabetic characters (case-sensitive) are potentially options.
 - If an equal sign "=" follows the first characters, unquoted, then the line is an option+value line.
 - If there is no equal sign, then the option will be treated like a bare flag.
- · Values are anything following the equals. Leading and trailing spaces are stripped, unless quoted.

Parameters

filespec	Provides the full path to the file to be processed.

Returns

Returns 'true' if any legal option was found, and 'false' if anything bad was found.

Definition at line 165 of file csvarray.cpp.

8.1.4.5 size_t midipp::csvarray::size() const [inline]

Accessor m_csv_lines.size()

Returns

Returns the number of VALUETYPE objects in the container.

Definition at line 184 of file csvarray.hpp.

8.1.5 Field Documentation

8.1.5.1 Rows midipp::csvarray::m_csv_lines [private]

Provides a section container.

All of the sections together specify all of the existing sections in an INI file.

Definition at line 84 of file csvarray.hpp.

8.1.5.2 bool midipp::csvarray::m_is_valid [private]

Indicates if construction succeeded in all respects.

An empty csvarray is not valid. Trying to read a non-existent or corrupt CSV file results in a csvarray that is not valid.

We're not big on throwing exceptions as a means of error handling.

Definition at line 107 of file csvarray.hpp.

8.1.5.3 char midipp::csvarray::m_separator [private]

Provides the value for the separator.

By default, this is a comma, but other characters, including a tab, can be used as well. The separator character can never be included in a Field.

Definition at line 64 of file csvarray.hpp.

The documentation for this class was generated from the following files:

- · csvarray.hpp
- · csvarray.cpp

8.2 midipp::initree Class Reference

This class provides a way to read and represent an INI file as a kind of tree structure that can be navigate to look up information.

#include <initree.hpp>

Collaboration diagram for midipp::initree:

```
midipp::stringmap<
      VALUETYPE >
   - m Name
    - m Fields
    + stringmap()
   + stringmap()
    + stringmap()
    + operator=()
    + ~stringmap()
   + name()
   + insert()
    + insert()
    + value()
    + clear()
   and 8 more...
   # name()
               -sm_dummy_section
      midipp::initree
- m_source_file
- m_name
- m_sections
- m_has_named_section
+ initree()
+ initree()
+ initree()
+ operator=()
+ ~initree()
+ name()
+ name()
+ insert()
+ section()
+ begin() and 6 more...
# readfile()
# section()
# clear()
# find()
# is_comment()
# process_section_name()
# process_option()
# make_section()
```

Public Types

- typedef midipp::stringmap< std::string > Section
 - Provides a handy name for the data structure that the initree class stores in a map.
- typedef std::map< std::string, Section > Container
 - Provides a type that holds a map of strings, keyed by strings.
- · typedef Container::const_iterator const_iterator

Provides a constant-iterator type for notational convenience.

· typedef Container::iterator iterator

Provides an iterator type for notational convenience.

typedef std::pair< std::string, Section > pair

Provides a pair type for notational convenience.

Public Member Functions

• initree ()

Creates an unnamed and empty initree.

• initree (const std::string &name, const std::string &filespec)

Creates a named, but empty, initree.

· initree (const initree &source)

Creates an unnamed and empty initree.

initree & operator= (const initree &source)

Creates an unnamed and empty initree.

virtual ~initree ()

Destructor

· const std::string & name () const

'Getter' function for member m_name

void name (const std::string &n)

'Setter' function for member m name

• int insert (const std::string §ionname, const Section §ion)

Allows the insertion of an stringmap object into the container.

const Section & section (const std::string §ionname) const

Provides a way to look up a section name and return a Section value, as a reference.

· const_iterator begin () const

Accessor m_sections.begin() const Makes this class look more like an STL container.

const_iterator end () const

Accessor m_sections.end() const Makes this class look more like an STL container.

iterator begin ()

Accessor m_sections.begin() This function makes this class look more like an STL container, good for using "for each" constructs.

• iterator end ()

Accessor m_sections.end() Makes this class look more like an STL container.

• size_t size () const

Accessor m_sections.size()

• bool empty () const

Accessor m_sections.empty()

const_iterator find (const std::string §ionname) const

Accessor m_sections.find() const Makes this class look more like an STL container.

Protected Member Functions

• bool readfile (const std::string &filespec)

Opens a file, and tries to construct an initree object, and a number of section objects, in it.

Section & section (const std::string §ionname)

Provides a way to look up a section name and return a Section value, as a reference.

· void clear ()

Allows the container to be emptied of Section objects.

• iterator find (const std::string §ionname)

Accessor m_sections.find() This function makes this class look more like an STL container.

bool is_comment (char c)

Checks for a comment character.

std::string process_section_name (const std::string &s, std::string::size_type p)

Extracts a section name, which must start with an alphabetic character, and can contain embedded spaces.

• bool process_option (const std::string &s, std::string::size_type p, const std::string §ionname)

Extracts an option from a line of text, where an option name must start with an alphabetic character, cannot have embedded spaces, and might not have a value.

bool make section (const std::string §ionname)

Created a new section, with the given name, and inserts it into the initree.

Private Attributes

std::string m_source_file

Provides the file-name of the file from which this tree of data was instantiated.

• std::string m_name

Provides the name of this object, for future reference.

· Container m sections

Provides a section container.

bool m_has_named_section

Indicates if any named sections were added to the tree.

Static Private Attributes

· static Section sm dummy section

Provides an empty section to use as a return value.

8.2.1 Detailed Description

This class provides a way to read and represent an INI file as a kind of tree structure that can be navigate to look up information.

An initree consists of Sections. A Section is a map of string values, keyed by the name of each value. A section can be named or un-named. There can be only one un-named section in an initree.

Definition at line 35 of file initree.hpp.

8.2.2 Member Typedef Documentation

8.2.2.1 typedef Container::const_iterator midipp::initree::const_iterator

Provides a constant-iterator type for notational convenience.

typedef typename Container::const_iterator const_iterator;

Definition at line 71 of file initree.hpp.

8.2.2.2 typedef std::map<std::string, Section> midipp::initree::Container

Provides a type that holds a map of strings, keyed by strings.

The string key is a section name. A section name comes from the "[Name]" token in an INI file.

The stringmap value is itself a map of strings, keyed by strings, where the key is the name of an option, and the value is the option's value. This pair comes from an entry in the INI file of the form "Name = Value".

Definition at line 63 of file initree.hpp.

8.2.2.3 typedef Container::iterator midipp::initree::iterator

Provides an iterator type for notational convenience.

typedef typename Container::iterator iterator;

Definition at line 81 of file initree.hpp.

8.2.2.4 typedef midipp::stringmap<std::string> midipp::initree::Section

Provides a handy name for the data structure that the initree class stores in a map.

Makes the code quite a bit easier to grok.

Note that Sections will generally have a name. However, an unnamed section is useful for representing INI files that have no section information.

Definition at line 49 of file initree.hpp.

8.2.3 Constructor & Destructor Documentation

```
8.2.3.1 midipp::initree::initree ( )
```

Creates an unnamed and empty initree.

The name can be added later with a call to name(), and sections can be added with the insert() function.

However, to simplify the code, the constructor always creates an unnamed section.

Definition at line 95 of file initree.cpp.

8.2.3.2 midipp::initree::initree (const std::string & name, const std::string & filespec)

Creates a named, but empty, initree.

The name can be added or modified later with a call to name(), and sections can be added with the insert() function.

If a file-name is given, the file is read to fill in the sections.

To simplify the code, the constructor always creates an unnamed section. If it isn't used, the overhead isn't significant.

Parameters

name	Provides the name of the initree object.
filespec	Provides the optional full path file-specification for the file to be opened and read to create all
	of the sections specified in that file.

Definition at line 124 of file initree.cpp.

8.2.3.3 midipp::initree::initree (const initree & source)

Creates an unnamed and empty initree.

The name can be added later with a call to name(), and sections can be added with the insert() function.

Definition at line 146 of file initree.cpp.

```
8.2.3.4 virtual midipp::initree::~initree( ) [inline],[virtual]
```

Destructor

Provided as a virtual destructor so that we can derive from this class.

Definition at line 141 of file initree.hpp.

8.2.4 Member Function Documentation

```
8.2.4.1 const_iterator midipp::initree::begin() const [inline]
```

Accessor m_sections.begin() const Makes this class look more like an STL container.

Returns

Returns a const iterator for the first element of the container, if any. Otherwise end() is returned.

Definition at line 211 of file initree.hpp.

```
8.2.4.2 iterator midipp::initree::begin() [inline]
```

Accessor m_sections.begin() This function makes this class look more like an STL container, good for using "for each" constructs.

Warning

Only a subset of std::map members are reimplemented in the stringmap class.

Returns

Returns an iterator for the first element of the container, if any. Otherwise end() is returned.

Definition at line 243 of file initree.hpp.

```
8.2.4.3 bool midipp::initree::empty ( ) const [inline]
```

Accessor m_sections.empty()

Returns

Returns true if the container is empty.

Definition at line 280 of file initree.hpp.

```
8.2.4.4 const_iterator midipp::initree::end( ) const [inline]
```

Accessor m_sections.end() const Makes this class look more like an STL container.

Returns

Returns a const iterator indicating the end of the container.

Definition at line 224 of file initree.hpp.

```
8.2.4.5 iterator midipp::initree::end() [inline]
```

Accessor m_sections.end() Makes this class look more like an STL container.

Returns

Returns an iterator indicating the end of the container.

Definition at line 256 of file initree.hpp.

```
8.2.4.6 const_iterator midipp::initree::find ( const std::string & sectionname ) const [inline]
```

Accessor m_sections.find() const Makes this class look more like an STL container.

Returns

Returns a const iterator for the found element of the container, if any. Otherwise end() is returned.

Definition at line 294 of file initree.hpp.

8.2.4.7 iterator midipp::initree::find (const std::string & sectionname) [inline], [protected]

Accessor m_sections.find() This function makes this class look more like an STL container.

Returns

Returns an iterator for the found element of the container, if any. Otherwise end() is returned.

Definition at line 349 of file initree.hpp.

8.2.4.8 int midipp::initree::insert (const std::string & sectionname, const Section & section) [inline]

Allows the insertion of an stringmap object into the container.

Parameters

section	The string that is to serve as the lookup value for the inserted object.
value	The value object to be added to the container.

Returns

The size of the container after insertion is returned. If important, the caller should check that the size is one larger.

Definition at line 179 of file initree.hpp.

8.2.4.9 bool midipp::initree::is_comment(char c) [inline], [protected]

Checks for a comment character.

Comment characters are:

- Hash mark "#". The comment character for shell scripts.
- Semicolon ";". The comment character for assembly language.
- Exclamation point "!" The comment character for Fluxbox configuration files..
- Single quote. The comment character for Visual BASIC.
- · Double quote. The comment character for vim scripts.

Parameters

С	The character to be checked.

Returns

Returns 'true' if the character is in the comment-character set.

Definition at line 373 of file initree.hpp.

8.2.4.10 bool midipp::initree::make_section (const std::string & sectionname) [protected]

Created a new section, with the given name, and inserts it into the initree.

Parameters

	Donatida a the manage of many anation that is to be asserted
sectionname	Provides the name of new section that is to be created.
0000.07.770	. To though the manner of them because that is to be discussed.

Returns

Returns 'true' if the section was successfully inserted into the initree.

Side-effect(s) If the created section has a name, then m_has_named_section is set to 'true'.

Definition at line 503 of file initree.cpp.

8.2.4.11 initree & midipp::initree::operator= (const initree & source)

Creates an unnamed and empty initree.

The name can be added later with a call to name(), and sections can be added with the insert() function.

Definition at line 163 of file initree.cpp.

8.2.4.12 bool midipp::initree::process_option (const std::string & s, std::string::size_type p, const std::string & sectionname) [protected]

Extracts an option from a line of text, where an option name must start with an alphabetic character, cannot have embedded spaces, and might not have a value.

This function handles options of the following forms:

```
option = value
option = "multiple-token value"
option = "multiple-token value"
option = ""

The legal characters in an option name are letters, digits, a hyphen
(minus), and underscore.

The "=" is mandatory, though the spaces around it are optional.

Every option has a string value. If the value is not provided, then
it is set to empty. If the string value is in double-quotes, it is
translated via snprintf(). Use double quites if spaces and special
characters are part of the string.

Comment characters other than single- or double-quotes end a value.
```

Parameters

S	Provides the current line of text, which starts with a letter.
р	Provides the position of the first letter.
currentsection	Points to the current Section (which might be an unnamed section). Option entries are added to this section. This pointer is checked elsewhere, and will not be null here unless we haven't yet hit a section. In that case, this function will created an unnamed section, if one does not yet exist.

Returns

Returns 'true' if the option was proper and properly processed. Otherwise, 'false' is returned.

Definition at line 376 of file initree.cpp.

```
8.2.4.13 std::string midipp::initree::process_section_name ( const std::string & s, std::string::size_type p) [protected]
```

Extracts a section name, which must start with an alphabetic character, and can contain embedded spaces.

This function processes a line of the follow formats to extract the section name:

```
[Name]
[ Name ]
[ Section Name ]

Leading and trailing spaces are not included in the section name.

Embedded spaces are included. Note that the trailing ']' is required, or the line is considered to be malformed.
```

Parameters

S	Provides the current line of text, which starts with '['.
р	Provides the position of the '[' character.

Returns

Returns the name of the newly-created section. If this name is empty, then an error occurred.

Definition at line 301 of file initree.cpp.

```
8.2.4.14 bool midipp::initree::readfile ( const std::string & filespec ) [protected]
```

Opens a file, and tries to construct an initree object, and a number of section objects, in it.

This function reads a file line by line.

- · Blank lines are skipped.
- Lines that start with ";", "#", "!", """, or double-quote are considered to be blank lines.
- Lines that start with "[" are potentially section-names; if not, then they are considered errors and processing fails.
- Lines that start with alphabetic characters (case-sensitive) are potentially options.
 - If an equal sign "=" follows the first characters, unquoted, then the line is an option+value line.
 - If there is no equal sign, then the option will be treated like a bare flag.
- · Values are anything following the equals. Leading and trailing spaces are stripped, unless quoted.

Parameters

filespec	Provides the full path to the file to be processed.
----------	---

Returns

Returns 'true' if any legal option was found, and 'false' if anything bad was found.

The code checks only for white-space characters; it is possible to embed control characters and have them treated as tokens. At your own risk, baby!

Definition at line 204 of file initree.cpp.

8.2.4.15 const Section& midipp::initree::section (const std::string & sectionname) const [inline]

Provides a way to look up a section name and return a Section value, as a reference.

This is the const version, meant for outsiders to use.

Parameters

sectionname	Provides the section name to be looked up.
-------------	--

Returns

Returns a constant reference to the Section found.

Definition at line 197 of file initree.hpp.

8.2.4.16 Section& midipp::initree::section (const std::string & sectionname) [inline], [protected]

Provides a way to look up a section name and return a Section value, as a reference.

Parameters

sectionname	Provides the section name to be looked up.

Returns

Returns a reference to the Section found. If it was not found, then a default-constructor (empty) Section is returned. It is the author's responsibility to check if the Section is useful or not.

Definition at line 322 of file initree.hpp.

```
8.2.4.17 size_t midipp::initree::size() const [inline]
```

Accessor m_sections.size()

Returns

Returns the number of VALUETYPE objects in the container.

Definition at line 268 of file initree.hpp.

8.2.5 Field Documentation

8.2.5.1 Container midipp::initree::m_sections [private]

Provides a section container.

All of the sections together specify all of the existing sections in an INI file.

Definition at line 109 of file initree.hpp.

```
8.2.5.2 initree::Section midipp::initree::sm_dummy_section [static], [private]
```

Provides an empty section to use as a return value.

Must provide an initialization for this static member of initree.

This dummy value helps us avoid the need for pointers.

Definition at line 122 of file initree.hpp.

The documentation for this class was generated from the following files:

- initree.hpp
- initree.cpp

8.3 midipp::midimapper Class Reference

This class provides for some basic remappings to be done to MIDI files, using the old and new facilities of libmidifilex.

#include <midimapper.hpp>

Collaboration diagram for midipp::midimapper:

midipp::midimapper

- + NOT_ACTIVE
- m_file_style
- m_setup_name
- m_map_type
- m_record_count
- m_gm_channel
- m device channel
- m_filter_channel
- m extraction on
- m rejection on
- m_map_reversed
- m_drum_map
- m patch map
- m_channel_map
- m_is_valid
- + midimapper()
- + midimapper()
- + repitch()
- + rechannel()
- + repatch()
- + file_style()
- + setup_name()
- + map_type()
- + record_count()
- + gm_channel()
- and 9 more...
- + active()
- + active()
- read_maps()
- read_unnamed_section()
- read_channel_section()

Public Member Functions

• midimapper ()

This constructor creates an unnamed, no-change mapping object.

midimapper (const std::string &filespec="", bool reverse_it=false, int filter_← channel=NOT ACTIVE, bool reject it=false)

This constructor creates an named mapping object, reading the mapping from an INI file.

• int repitch (int channel, int input)

Changes a note value based on the note-mapping that was provided.

• int rechannel (int channel)

Changes a channel value based on the channel-mapping that was provided.

• int repatch (int program)

Changes a program/patch value based on the patch-mapping that was provided.

const std::string & file_style () const

'Getter' function for member m_file_style

• const std::string & setup_name () const

'Getter' function for member m_setup_name

const std::string & map_type () const

'Getter' function for member m_map_type

• int record_count () const

'Getter' function for member m_record_count

• int gm_channel () const

'Getter' function for member m gm channel

• int device_channel () const

'Getter' function for member m device channel

• int filter_channel () const

'Getter' function for member m_filter_channel

• bool extract () const

'Getter' function for member m_extraction_on

· bool reject () const

'Getter' function for member m_rejection_on

· bool valid () const

'Getter' function for member m_is_valid;

const std::map< int, int > & drum_map () const

'Getter' function for member m_drum_map Returns a reference to the note map.

const std::map< int, int > & patch_map () const

'Getter' function for member m_patch_map Returns a reference to the patch map.

const std::map< int, int > & channel_map () const

'Getter' function for member m_channel_map Returns a reference to the channel map.

bool map_reversed () const

'Getter' function for member m_map_reversed

Static Public Member Functions

• static bool active (int value)

Determines if the value parameter is usable, or "active".

• static bool active (int v1, int v2)

Determines if both value parameters are usable, or "active".

Static Public Attributes

• static const int NOT ACTIVE = -1

Provides a constant to indicate an inactive or invalid integer value.

Private Member Functions

bool read maps (const std::string &filename)

Creates an integer mapping map from the given INI file.

bool read_unnamed_section (const initree &it)

This function searches through the unnamed section at the top of the file.

• bool read_channel_section (const initree &it)

This function searches through the Channel section, if it exists.

Private Attributes

• std::string m_file_style

Provides the style of the INI file.

• std::string m_setup_name

Provides a nice tag name for the setup, nothing more.

std::string m_map_type

Indicates what kind of mapping is allegedly provided by the file.

· int m record count

Provides the number of records (lines) or sections in the INI file.

int m_gm_channel

Provides the channel to use for General MIDI drums.

· int m device channel

Provides the channel that is used by the native device.

• int m_filter_channel

Provides an optional channel number to filter in the MIDI file.

bool m_extraction_on

A faster way to check if m_filter_channel is enabled.

bool m_rejection_on

Changes the extraction-channel to a rejection channel, where only the channel that matches is dropped from the output MIDI file.

· bool m map reversed

Indicates that the mapping should occur in the reverse direction.

std::map< int, int > m_drum_map

Provides the mapping between pitches.

std::map< int, int > m_patch_map

Provides the mapping between patches (programs).

std::map< int, int > m_channel_map

Provides the mapping between channels (optional).

• bool m is valid

Indicates if the setup is valid.

8.3.1 Detailed Description

This class provides for some basic remappings to be done to MIDI files, using the old and new facilities of libmidifilex.

It works by holding all sorts of standard C++ map objects that are used to translate from one numeric value to another.

For use in the midicvtpp application, a single global instance of this object is created, and is used in static C-style callback functions that can be used in the C library libmidifilex.

Definition at line 109 of file midimapper.hpp.

8.3.2 Constructor & Destructor Documentation

8.3.2.1 midipp::midimapper::midimapper ()

This constructor creates an unnamed, no-change mapping object.

This object can be used for testing.

Definition at line 83 of file midimapper.cpp.

8.3.2.2 midipp::midimapper::midimapper (const std::string & name, const std::string & filespec = " ", bool reverse_it = false, int filter_channel = NOT_ACTIVE, bool reject_it = false)

This constructor creates an named mapping object, reading the mapping from an INI file.

This object can be used for testing.

Parameters

name	Provides a handy name to refer to when reading the output of this object.
filespec	Provides the full file-path specification of an INI-style file to be read. See the example files in
	the tests/inifiles directory.
reverse_it	Indicates if the numeric values are to be swapped. Thus, applying the MIDI mapper operation
	for a given INI file, and then reversing it, should yield something like the original MIDI file.
filter_channel	Provides a single channel to be treated specially, being either saved alone, or dropped from
	the MIDI file. This value should range from 1 to 16, and is converted internally to the 0 to
	15 range. The default value is NOT_ACTIVE (-1), which means no channel filtering is to be
	done.
reject_it	If the filter_channel is valid, this boolean parameter indicates that the channel is to be dropped
	from the output MIDI file. If false (the default value), the channel is the only one kept in the
	output MIDI file.

Definition at line 138 of file midimapper.cpp.

8.3.3 Member Function Documentation

8.3.3.1 static bool midipp::midimapper::active (int *value*) [inline], [static]

Determines if the value parameter is usable, or "active".

Parameters

value	The integer value to be checked.

Returns

Returns true if the value is not NOT_ACTIVE.

Definition at line 316 of file midimapper.hpp.

8.3.3.2 static bool midipp::midimapper::active (int v1, int v2) [inline], [static]

Determines if both value parameters are usable, or "active".

Parameters

v1	The first integer value to be checked.
v2	The second integer value to be checked.

Returns

Returns true if both of the values are not NOT ACTIVE.

Definition at line 334 of file midimapper.hpp.

8.3.3.3 const std::map<int, int>& midipp::midimapper::drum_map() const [inline]

'Getter' function for member m_drum_map Returns a reference to the note map.

The weird thing was that, when I had left the reference operator out, show_note_map() would show a lot of notes missing from the map, as if copying the map wasn't working properly!!!

Definition at line 441 of file midimapper.hpp.

8.3.3.4 bool midipp::midimapper::read_channel_section (const initree & it) [private]

This function searches through the Channel section, if it exists.

Each entry must be of the following format, or an error will occur:

 $ch_01 = 10$

Parameters

it Provides the tree of INI name/value pairs to analyze.

Returns

Returns true if there was no channel section to bother with, or it there was, and the processing of it succeeded. This function assumes the read_unnamed_section() function was already called, and succeeded.

Definition at line 474 of file midimapper.cpp.

8.3.3.5 bool midipp::midimapper::read_maps (const std::string & filename) [private]

Creates an integer mapping map from the given INI file.

An initree object is temporarily created in order to read the file and provide the settings we need. We don't need to use shared-pointers, since this function is written in a safe manner.

This function iterates through the sections. Note than an unnamed section is treated differently: The "gm-channel" and "dev-channel" values are looked up and set.

Inserts the pair of (gm_note, device_note), depending on the m_map_reversed flag. If false (the normal case), then we want the key to be the gm_note, and the value to be the device_note. That is, given a MIDI file scored for a non-GM device, we want the notes to be remapped to the notes that GM needs to make a the sound intended by the device-note.

If the m_map_reversed flag is true, then we want to take a GM MIDI file and re-map it for the corresponding device note.

Parameters

illeriarne Provides the full path specification of the file to be read.	filename	Provides the full path specification of the file to be read.
---	----------	--

Returns

Returns true if the operation succeeded.

Definition at line 202 of file midimapper.cpp.

8.3.3.6 bool midipp::midimapper::read_unnamed_section(const initree & it) [private]

This function searches through the unnamed section at the top of the file.

Note than an unnamed section is treated differently: The "gm_channel" and "device_channel" values are looked up and set.

Parameters

it | Provides the tree of INI name/value pairs to analyze.

Returns

Returns true if the whole tree has any elements. If it has an unnamed section, then 'true' also indicates that no errors occurred in processing those values.

Definition at line 357 of file midimapper.cpp.

8.3.3.7 int midipp::midimapper::rechannel (int channel)

Changes a channel value based on the channel-mapping that was provided.

Note that there are actually two possible channel-mappings. The first one is based on the values of gm-channel and dev-channel, and is used to map drum tracks (e.g. from channel 16 to channel 10). The second mapping allows more general mapping, and is applied only if the channel isn't affected by the drum mapping. The second form is specified by the "[Channels]" section.

The reversal option is accounted for at setup time for both of these types of mappings, as was done for the drum (note) value mappings.

If the m_filter_channel value is valid (between 0 and 15), and the input channel does *not* match this value, then -1 (midimapper::NOT_ACTIVE) is returned to indicate to reject the event.

Parameters

channel Provides the value of the input channel, as obtained from the input MIDI file.

Returns

Returns one of the following values:

- The output channel value corresponding to the input channel value if the input channel matches m_{_}
 —
 gm_channel, and m_gm_channel is set.
- The original input channel if the input channel is not one that matches m_gm_channel in the channel mapping, or if m_gm_channel is not activated (i.e. set to -1 [NOT_ACTIVE]).
- NOT_ACTIVE (-1) is returned if the input channel doesn't match m_filter_channel and m_extraction_on is true. In other words, only one channel is allowed to be output
- NOT_ACTIVE (-1) is returned if the input channel does match m_filter_channel and m_rejection_on is true. In other words, one channel is systematically rejected from the output.

Only if m_gm_channel and m_device_channel have been set are they used to detect and alter the channel number of the event. If they aren't active, or if the channel isn't the drum channel to be remapped, then the "[Channels]" map is checked.

Definition at line 613 of file midimapper.cpp.

8.3.3.8 int midipp::midimapper::repatch (int *program*)

Changes a program/patch value based on the patch-mapping that was provided.

Since the reversal option for note values is set up during the construction of the note map, the m_map_reversed flag does not need to be checked in this function.

Parameters

program	Provides the value of the input patch, as obtained from the input MIDI file.

Returns

Returns the output patch value corresponding to the input patch value. If the input patch is not found in the map, it is returned unaltered. The map is empty if an empty INI file-name was passed to the constructor.

Definition at line 666 of file midimapper.cpp.

8.3.3.9 int midipp::midimapper::repitch (int channel, int input)

Changes a note value based on the note-mapping that was provided.

Since the reversal option for note values is set up during the construction of the note map, the m_map_reversed flag does not need to be checked in this function.

Parameters

channel	Provides the channel for the input note. Only if the channel matches the one channel to be
	remapped, will repitching occur.

input | Provides the value of the input note, as obtained from the input MIDI file.

Returns

Returns the output note value corresponding to the input note value. If the input note is not found in the map, it is returned unaltered. The map is empty if an empty INI file-name was passed to the constructor.

Definition at line 562 of file midimapper.cpp.

8.3.4 Field Documentation

8.3.4.1 std::map<int, int> midipp::midimapper::m_channel_map [private]

Provides the mapping between channels (optional).

If m_map_reversed is true, then the mapping of channels is reversed.

Definition at line 282 of file midimapper.hpp.

8.3.4.2 int midipp::midimapper::m_device_channel [private]

Provides the channel that is used by the native device.

Older MIDI equipment sometimes used channel 16 for percussion.

The name of this attribute in the INI file is "dev-channel". Case is significant.

Definition at line 204 of file midimapper.hpp.

8.3.4.3 std::map<int, int> midipp::midimapper::m_drum_map [private]

Provides the mapping between pitches.

If m_map_reversed is false, then the key is the GM pitch/note, and the value is the device pitch/note (which is the GM note needed to produce the same sound in GM as the device would have produced). If m_map_reversed is true, then the key is the GM pitch/note, and the value is the device pitch/note, so that the MIDI file will be converted from GM mapping to device mapping.

Definition at line 262 of file midimapper.hpp.

8.3.4.4 std::string midipp::midimapper::m file style [private]

Provides the style of the INI file.

This is one of the following strings:

- "simple". All of the mapping information is contained in a single comma-separated value. We probably won't end up supporting this option, as it is a bit harder for humans to read. See doc/GM_PSS-790_← Drums-save.ini.
- "sectioned". The mapping information for each note is contained in its own "Drum" section. See doc/GM← _PSS-790_Drums.ini.

The name of this attribute in the INI file is "file-style". Case is significant.

Definition at line 139 of file midimapper.hpp.

8.3.4.5 int midipp::midimapper::m_filter_channel [private]

Provides an optional channel number to filter in the MIDI file.

If this value is specified, then one of two kinds of channel filtering is turned on:

1. If m_extraction_on is true, then only channel-based events on the filtered channel will be written to the output MIDI file.

2. If m_rejection_on is true, then only channel-based events *not* on the filtered channel will be written to the output MIDI file.

This attribute is called "extract-channel" or "reject-channel". This is a command-line option. By default this value is -1, which means to not filter by channel.

Definition at line 223 of file midimapper.hpp.

8.3.4.6 int midipp::midimapper::m_gm_channel [private]

Provides the channel to use for General MIDI drums.

This value is usually 9, meaning MIDI channel 10. However, be careful, as externally, this value is always on a 1-16 scale, while internally it is reduced by 1 (a 0-15 scale) to save endless decrements.

The name of this attribute in the INI file is "gm-channel". Case is significant.

Definition at line 194 of file midimapper.hpp.

8.3.4.7 bool midipp::midimapper::m_map_reversed [private]

Indicates that the mapping should occur in the reverse direction.

That is, instead of mapping the notes from the device pitches and channel to General MIDI, the notes and channel should be mapped from General MIDI back to the device. This option is useful for playing back General MIDI files on old equipment.

Note that this option is an INI option ("reverse"), as well as a command-line option. It is specified by alternate means, such as a command-line parameter like "--reverse".

Definition at line 250 of file midimapper.hpp.

8.3.4.8 std::string midipp::midimapper::m_map_type [private]

Indicates what kind of mapping is allegedly provided by the file.

This can be one of the following values:

- "drum". The file describes mapping one pitch/channel to another pitch/channel, used mostly for coercing old drum machines to something akin to a General MIDI kit.
- "patch". The file describes program (patch) mappings, used to map old devices patch change values to General MIDI.
- "multi". The file describes both "drum" and "patch" mappings.

The name of this attribute in the INI file is "map-type". Case is significant.

Definition at line 168 of file midimapper.hpp.

8.3.4.9 std::map<int, int> midipp::midimapper::m_patch_map [private]

Provides the mapping between patches (programs).

If m_map_reversed is false, then the key is the GM patch/program, and the value is the device patch/program (which is the GM note needed to produce the same sound in GM as the device would have produced). If m_map_reversed is true, then the key is the GM patch/program, and the value is the device patch/program so that the MIDI file will be converted from GM mapping to device mapping.

Definition at line 275 of file midimapper.hpp.

 $\textbf{8.3.4.10} \quad \textbf{int midipp::midimapper::m_record_count} \quad \texttt{[private]}$

Provides the number of records (lines) or sections in the INI file.

Indicates the number of items being remapped.

This attribute ("record-count") does not appear in the INI file, as it is calculated as the file is read.

Warning

Only applies to "drum" mappings at present. MUST FIX!

Definition at line 181 of file midimapper.hpp.

8.3.4.11 std::string midipp::midimapper::m_setup_name [private]

Provides a nice tag name for the setup, nothing more.

It can be anything. A common value is the name of the program that the INI file is meant for.

The name of this attribute in the INI file is "setup-name". Case is significant.

Definition at line 150 of file midimapper.hpp.

The documentation for this class was generated from the following files:

- · midimapper.hpp
- · midimapper.cpp

8.4 midipp::stringmap< VALUETYPE > Class Template Reference

Provides an std::map wrapper geared towards using std::string as a key.

#include <stringmap.hpp>

Collaboration diagram for midipp::stringmap < VALUETYPE >:

midipp::stringmap< VALUETYPE > - m Name - m Fields + stringmap() + stringmap() + stringmap() + operator=() + ~stringmap() + name() + insert() + insert() + value() + clear() and 8 more... # name()

Public Types

- typedef std::map< std::string, VALUETYPE > Container
 Defines the type of container used by stringmap.
- typedef Container::const_iterator const_iterator
 Provides a constant-iterator type for notational convenience.

typedef Container::iterator iterator

Provides an iterator type for notational convenience.

typedef std::pair< std::string, VALUETYPE > pair

Provides a pair type for notational convenience.

Public Member Functions

• stringmap ()

Default constructor Creates an empty and unnamed Container.

• stringmap (const std::string &name)

Default constructor Creates an empty, but named Container.

• stringmap (const stringmap &source)

Copy constructor Copies the Container.

stringmap & operator= (const stringmap &source)

Principal Assignment Operator

virtual ∼stringmap ()

Destructor

· const std::string & name () const

'Getter' function for member m_Name

int insert (const std::string &key, const VALUETYPE &value)

Allows the insertion of a VALUETYPE object into the container.

int insert (const VALUETYPE &value)

Manufacturers a new key based on the current size of the container, and inserts the given value with this key.

• VALUETYPE value (const std::string &key) const

Provides a way to look up a string key and return a value.

• void clear ()

Allows the container to be emptied of VALUETYPE objects.

· iterator begin ()

Accessor m_Fields.begin() This function makes this class look more like an STL container, good for using "for each" constructs.

· const_iterator begin () const

Accessor m_Fields.begin() const Makes this class look more like an STL container.

• iterator end ()

Accessor m_Fields.end() Makes this class look more like an STL container.

· const iterator end () const

Accessor m_Fields.end() const Makes this class look more like an STL container.

• size_t size () const

Accessor m_Fields.size()

· bool empty () const

Accessor m_Fields.empty()

iterator find (const std::string &key)

Accessor m_Fields.find() This function makes this class look more like an STL container.

const_iterator find (const std::string &key) const

Accessor m_Fields.find() const Makes this class look more like an STL container.

Protected Member Functions

• void name (const std::string &n)

'Setter' function for member m_Name

Private Attributes

std::string m_Name

Provides the name of the stringmap.

· Container m Fields

Provides the actual container for which the stringmap template class is a wrapper.

8.4.1 Detailed Description

template < class VALUETYPE > class midipp::stringmap < VALUETYPE >

Provides an std::map wrapper geared towards using std::string as a key.

The problem with using integers is that they are not very easy to decipher while debugging, nor are they easy to understand in code (without using ugly define-macros).

Also, strings are a frequent lookup mechanism. A wrapper is needed so that we can disable the automatic insertion of objects that occurs when operator [] is applied to a key that does not yet exist in the std::map container.

Efficiency? Well, we should test that. :-) We're using copy semantic for the value part. If you use pointers for the value, the management of them is up to you!

This template class supports looking up a container of VALUETYPE objects by std::string.

The VALUETYPE must support and publicize the following operations:

- Default constructor. In addition, the default constructor should create an object that indicates an error state. This feature is necessary so that we can avoid throwing exceptions when doing map lookups.
- · Copy constructor.
- · Principal assignment operator.
- show(). The object must have its own overload of the global show() function. See the stringmap.cpp module.

The type of container is given by the Container typedef. The stringmap template is essentially a wrapper for this class.

- Consider implementing lookup by integer index; right now, iterators suffice;
 - It would be nice to be able to superimpose a numeric order on the container, somehow.

Definition at line 82 of file stringmap.hpp.

8.4.2 Member Typedef Documentation

8.4.2.1 template < class VALUETYPE > typedef std::map < std::string, VALUETYPE > midipp::stringmap < VALUETYPE >::Container

Defines the type of container used by stringmap.

We want to be able to use array notation, yet be able to look up items (e.g. database fields) by name.

Definition at line 94 of file stringmap.hpp.

8.4.3 Constructor & Destructor Documentation

8.4.3.1 template < class VALUETYPE > midipp::stringmap < VALUETYPE >::stringmap (const stringmap < VALUETYPE > & source) [inline]

Copy constructor Copies the Container.

Parameters

source	The stringmap to be copied.
--------	-----------------------------

Definition at line 162 of file stringmap.hpp.

8.4.3.2 template < class VALUETYPE > virtual midipp::stringmap < VALUETYPE >::~stringmap () [inline], [virtual]

Destructor

Provided as a virtual destructor so that we can derive from this class.

Definition at line 198 of file stringmap.hpp.

8.4.4 Member Function Documentation

8.4.4.1 template < class VALUETYPE > iterator midipp::stringmap < VALUETYPE >::begin () [inline]

Accessor m_Fields.begin() This function makes this class look more like an STL container, good for using "for each" constructs.

Warning

Only a subset of std::map members are reimplemented in the stringmap class.

Returns

Returns an iterator for the first element of the container, if any. Otherwise end() is returned.

Definition at line 306 of file stringmap.hpp.

8.4.4.2 template < class VALUETYPE > const_iterator midipp::stringmap < VALUETYPE > ::begin () const [inline]

Accessor m_Fields.begin() const Makes this class look more like an STL container.

Returns

Returns a const iterator for the first element of the container, if any. Otherwise end() is returned.

Definition at line 320 of file stringmap.hpp.

8.4.4.3 template < class VALUETYPE > bool midipp::stringmap < VALUETYPE > ::empty () const [inline]

Accessor m_Fields.empty()

Returns

Returns true if the container is empty.

Definition at line 370 of file stringmap.hpp.

8.4.4.4 template < class VALUETYPE > iterator midipp::stringmap < VALUETYPE >::end() [inline]

Accessor m_Fields.end() Makes this class look more like an STL container.

Returns

Returns an iterator indicating the end of the container.

Definition at line 333 of file stringmap.hpp.

8.4.4.5 template < class VALUETYPE > const_iterator midipp::stringmap < VALUETYPE > ::end () const [inline]

Accessor m Fields.end() const Makes this class look more like an STL container.

Returns

Returns a const iterator indicating the end of the container.

Definition at line 346 of file stringmap.hpp.

8.4.4.6 template < class VALUETYPE > iterator midipp::stringmap < VALUETYPE >::find (const std::string & key) [inline]

Accessor m Fields.find() This function makes this class look more like an STL container.

Returns

Returns an iterator for the found element of the container, if any. Otherwise end() is returned.

Definition at line 384 of file stringmap.hpp.

8.4.4.7 template < class VALUETYPE > const_iterator midipp::stringmap < VALUETYPE >::find (const std::string & key) const [inline]

Accessor m_Fields.find() const Makes this class look more like an STL container.

Returns

Returns a const iterator for the found element of the container, if any. Otherwise end() is returned.

Definition at line 398 of file stringmap.hpp.

8.4.4.8 template < class VALUETYPE > int midipp::stringmap < VALUETYPE >::insert (const std::string & key, const VALUETYPE & value) [inline]

Allows the insertion of a VALUETYPE object into the container.

Parameters

key	The string that is to serve as the lookup value for the inserted object.
value	The value object to be added to the container.

Returns

The size of the container after insertion is returned. If important, the caller should check that the size is one larger.

Definition at line 227 of file stringmap.hpp.

8.4.4.9 template < class VALUETYPE > int midipp::stringmap < VALUETYPE >::insert (const VALUETYPE & value) [inline]

Manufacturers a new key based on the current size of the container, and inserts the given value with this key.

This function is meant to parallel the integer-key version of the insert() function. It could also be called append().

Parameters

value	The value object to be added to the container.
-------	--

Returns

The size of the container after insertion is returned.

Definition at line 247 of file stringmap.hpp.

8.4.4.10 template < class VALUETYPE > stringmap& midipp::stringmap < VALUETYPE >::operator= (const stringmap < VALUETYPE > & source) [inline]

Principal Assignment Operator

Copies one Container into the current object's Container.

Parameters

	,
source	The stringmap to be copied into the current stringmap.

Returns

A reference to the destination object is returned, in order to support multiple assignments in one statement.

Definition at line 182 of file stringmap.hpp.

8.4.4.11 template < class VALUETYPE > size_t midipp::stringmap < VALUETYPE > ::size () const [inline]

Accessor m Fields.size()

Returns

Returns the number of VALUETYPE objects in the container.

Definition at line 358 of file stringmap.hpp.

8.4.4.12 template < class VALUETYPE > VALUETYPE midipp::stringmap < VALUETYPE >::value (const std::string & key) const [inline]

Provides a way to look up a string key and return a value.

We can't just return "m_Fields[key]" because that causes an insertion if the key doesn't exist in the map. That is not the semantics we want.

Note

This statement can change the container, so is not const.

return m_Fields[key];

Parameters

key	Provides the string key to be looked up.

Returns

Returns the VALUETYPE found. If it was not found, then a default-constructor VALUETYPE is returned. It is the author's responsibility to provide an error-checking facility in VALUETYPE.

Definition at line 274 of file stringmap.hpp.

8.4.5 Field Documentation

8.4.5.1 template < class VALUETYPE > std::string midipp::stringmap < VALUETYPE >:::m_Name [private]

Provides the name of the stringmap.

This name can be used to add the stringmap to a stringmap full of stringmaps.

Definition at line 123 of file stringmap.hpp.

The documentation for this class was generated from the following file:


· stringmap.hpp

9 File Documentation

9.1 csvarray.cpp File Reference

Primitive, but useful, CSV-file input parser.

```
#include <fstream>
#include <csvarray.hpp>
Include dependency graph for csvarray.cpp:
```



Macros

• #define TOKEN_SPACES " \t\0"

Provides a consistent definition of the whitespace characters.

Functions

• void show (const std::string &tag, const midipp::csvarray &container)

Writes out the contents of the csvarray container to stderr.

9.1.1 Detailed Description

Primitive, but useful, CSV-file input parser.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-23

Last Edits 2014-05-21

Version

\$Revision\$ License \$XPC_SUITE_GPL_LICENSE\$

Provides a way to convert a simple CSV (comma-separated value) file into an array of data.

Warning

1. This module assumes only ASCII text. This is a big limitation for internationalization.

9.1.2 Macro Definition Documentation

9.1.2.1 #define TOKEN_SPACES " \t\0"

Provides a consistent definition of the whitespace characters.

This define does not bother to try to trap all the characters that could be considered whitespace or outside the range of legal section and option names.

Definition at line 32 of file csvarray.cpp.

9.1.3 Function Documentation

9.1.3.1 void show (const std::string & tag, const midipp::csvarray & container)

Writes out the contents of the csvarray container to stderr.

This implementation is a for_each style of looping through the container.

Parameters

tag	Identifies the object in the human-readable output.
container	The stringmap through which iteration is done for showing.


Definition at line 240 of file csvarray.cpp.

9.2 csvarray.hpp File Reference


Library libmidipp

```
#include <string>
#include <vector>
```

Include dependency graph for csvarray.hpp:



This graph shows which files directly or indirectly include this file:



Data Structures

· class midipp::csvarray

The csvarray class assist in parsing a file that has lines of comma-separated values.

Functions

void show (const std::string &tag, const midipp::csvarray &container)
 Writes out the contents of the csvarray container to stderr.

9.2.1 Detailed Description

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-23

Last Edits 2014-05-21

Version

\$Revision\$ License \$MIDIPP_SUITE_GPL_LICENSE\$

Provides a way to convert a simple CSV (comma-separated value) file into an array of data, and into an INI format.

The input CSV file is an unadorned file. The caller must know what the file is for, so that the results can be properly annotated.

9.2.2 Function Documentation

9.2.2.1 void show (const std::string & tag, const midipp::csvarray & container)

Writes out the contents of the csvarray container to stderr.

This implementation is a for_each style of looping through the container.

Parameters

tag	Identifies the object in the human-readable output.
container	The stringmap through which iteration is done for showing.


Definition at line 240 of file csvarray.cpp.

9.3 ininames.hpp File Reference


Provides some free functions to write INI files, given a midipp::csvarray object.

#include <string>

Include dependency graph for ininames.hpp:



This graph shows which files directly or indirectly include this file:



Enumerations

enum gm_ini_section_t {
 midipp::INI_SECTION_DRUM,
 midipp::INI_SECTION_PATCH,
 midipp::INI_SECTION_CHANNEL,
 midipp::INI_SECTION_UNKNOWN }

Provides a selection switch for the supported INI section types.

Variables

• const std::string midipp::DRUM SECTION = "Drum"

Provides the prefix for the initial part of the drum-section name.

const std::string midipp::DRUM LABEL GM NAME = "gm-name"

Provides the string for the name of the DRUM_INDEX_GM_NAME field as shown in the INI file.

const std::string midipp::DRUM_LABEL_GM_NOTE = "gm-note"

Provides the string for the name of the DRUM_INDEX_GM_NOTE field as shown in the INI file.

const std::string midipp::DRUM_LABEL_DEV_NAME = "dev-name"

Provides the string for the name of the DRUM_INDEX_DEV_NAME field as shown in the INI file.

• const std::string midipp::DRUM_LABEL_DEV_NOTE = "dev-note"

Provides the string for the name of the DRUM_INDEX_DEV_NAME field as shown in the INI file.

const std::string midipp::DRUM LABEL GM EQUIV = "gm-equiv"

Provides the string for the name of the DRUM_INDEX_GM_EQUIV field as shown in the INI file.

const std::string midipp::PATCH_SECTION = "Patch"

Provides the prefix for the initial part of the patch-section name.

const std::string midipp::PATCH_LABEL_GM_NAME = "gm-name"

Provides the string for the name of the PATCH INDEX GM NAME field as shown in the INI file.

• const std::string midipp::PATCH LABEL GM PATCH = "gm-patch"

Provides the string for the name of the PATCH_INDEX_GM_PATCH field as shown in the INI file.

const std::string midipp::PATCH_LABEL_DEV_NAME = "dev-name"

Provides the string for the name of the PATCH_INDEX_DEV_NAME field as shown in the INI file.

const std::string midipp::PATCH_LABEL_DEV_PATCH = "dev-patch"

Provides the string for the name of the PATCH_INDEX_DEV_NAME field as shown in the INI file.

const std::string midipp::PATCH_LABEL_GM_EQUIV = "gm-equiv"

Provides the string for the name of the PATCH_INDEX_GM_EQUIV field as shown in the INI file.

const std::string midipp::CHANNEL_SECTION = "Channels"

Provides the prefix for the channel-section name.

• const std::string midipp::CHANNEL_TOKEN = "ch_"

Provides the initial part of the name for each entry in the channel-section.

• const std::string midipp::GM_INI_FILE_STYLE = "file-style"

Provides a consistent string for the file-style attribute.

const std::string midipp::GM_INI_SETUP_NAME = "setup-name"

Provides a consistent string for the setup-name attribute.

• const std::string midipp::GM_INI_MAP_TYPE = "map-type"

Provides a consistent string for the map-type attribute.

const std::string midipp::GM_INI_GM_CHANNEL = "gm-channel"

Provides a consistent string for the GM-channel attribute.

const std::string midipp::GM_INI_DEV_CHANNEL = "dev-channel"

Provides a consistent string for the device-channel attribute.

const std::string midipp::GM_INI_EXTRACT_CHANNEL = "extract-channel"

Provides a consistent string for the extract-channel attribute.

• const std::string midipp::GM_INI_REJECT_CHANNEL = "reject-channel"

Provides a consistent string for the reject-channel attribute.

• const std::string midipp::GM_INI_REVERSE = "reverse"

Provides a consistent string for the reverse attribute.

const std::string midipp::GM_INI_TESTING = "testing"

Provides a consistent string for the testing attribute.

const std::string midipp::GM_INI_NO_VALUE = "none"

Provides a consistent string for the "none" value.

9.3.1 Detailed Description

Provides some free functions to write INI files, given a midipp::csvarray object.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-05-06

Last Edits 2014-05-17

Version

\$Revision\$ License \$XPC_SUITE_GPL_LICENSE\$

Provides a way to write various kinds of MIDI-related INI files.


Also provides some names and macros.

9.4 initree.cpp File Reference

Primitive INI-file input parser derived from the XPC library.

```
#include <cctype>
#include <fstream>
#include <initree.hpp>
```

Include dependency graph for initree.cpp:



Functions

void show (const std::string &tag, const midipp::initree &container)
 Writes out the contents of the stringmap container.

9.4.1 Detailed Description

Primitive INI-file input parser derived from the XPC library.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-22

Last Edits 2014-05-21

Version

\$Revision\$ License \$XPC_SUITE_GPL_LICENSE\$

Provides a way to set the application options from a Windows-style "INI" file, by parsing that configuration file and making it available as if it were a set of command-line parameters.

The file is in simple INI format. Each line is one of the following:

- · Blank. Blank lines are ignored.
- Comment. Lines whose first non-white-space character is one of hash-mark, semi-colon, exclamation-point, single-quote, or double-quote, are ignored.
- Section. "[Section Name]". If present, this item is used to indicate which group of initializations are acceptable to the caller.
- Option + value. optioname = optionvalue.

· Option without value. This item is treated like a simple flag, since there is no value specified.

Warning

- 1. This module assumes only ASCII text. This is a big limitation and severely hurts internationalization.
- 2. The code cannot really handle mixes of quotes and comment characters on an option line. So, generally prefer blocks of comments between options, rather than trailing comments on an option line. See the tests/initree.ini file.
- 3. Comments are not saved anywhere, so when we get around to writing out an INI file, they will get dropped.

9.4.2 Function Documentation

9.4.2.1 void show (const std::string & tag, const midipp::initree & container)

Writes out the contents of the stringmap container.

This implementation is a for each style of looping through the container.

Parameters


tag	Identifies the object in the human-readable output.
container	The stringmap through which iteration is done for showing.

Definition at line 533 of file initree.cpp.


9.5 initree.hpp File Reference

Provides a "tree" that represents an INI file with named and unnamed sections, and name/value pairs.

#include <stringmap.hpp>
Include dependency graph for initree.hpp:



This graph shows which files directly or indirectly include this file:



Data Structures

· class midipp::initree

This class provides a way to read and represent an INI file as a kind of tree structure that can be navigate to look up information.

Functions

void show (const std::string &tag, const midipp::initree &container)
 Writes out the contents of the stringmap container.

9.5.1 Detailed Description

Provides a "tree" that represents an INI file with named and unnamed sections, and name/value pairs.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-22

Last Edits 2014-05-21

Version

\$Revision\$ License \$MIDIPP_SUITE_GPL_LICENSE\$

Provides a way to create an options tree using a DOS/Windows INI-style configuration file.

9.5.2 Function Documentation

9.5.2.1 void show (const std::string & tag, const midipp::initree & container)

Writes out the contents of the stringmap container.

This implementation is a for_each style of looping through the container.

Parameters


tag	Identifies the object in the human-readable output.
container	The stringmap through which iteration is done for showing.

Definition at line 533 of file initree.cpp.

9.6 iniwriting.cpp File Reference

Provides some free functions to write INI files, given a midipp::csvarray object.

```
#include <fstream>
#include <csvarray.hpp>
#include <ininames.hpp>
#include <iniwriting.hpp>
Include dependency graph for iniwriting.cpp:
```



Macros

#define _NL std::endl /* defined for brevity/formatting */
 Provides a less cluttered way to add a newline to string output.

Functions

- bool midipp::write_simple_drum_file (const std::string &filespec, const csvarray &csv)

 Writes a csvarray object to a file in a simple INI format.
- bool midipp::write_sectioned_drum_file (const std::string &filespec, const csvarray &csv, bool writefooter)

 Writes a csvarray object to a drum file in a sectioned INI format.
- bool midipp::write_sectioned_patch_file (const std::string &filespec, const csvarray &csv, bool write-header)

Writes a csvarray object to a patch file in a sectioned INI format.

Variables

static const std::string midipp::s_explanatory_header
 Provides explanatory text for the top of the INI file.

Generated on Thu Aug 20 2015 06:24:59 for MIDIcvt Developer's Reference Manual by Doxygen

9.6.1 Detailed Description

Provides some free functions to write INI files, given a midipp::csvarray object.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-23

Last Edits 2014-05-21

Version

\$Revision\$ License \$XPC_SUITE_GPL_LICENSE\$


Provides a way to create INI files from the contents of a midipp::csvarray object.

9.7 iniwriting.hpp File Reference


Provides some free functions to write INI files, given a midipp::csvarray object.

#include <string>

Include dependency graph for iniwriting.hpp:



This graph shows which files directly or indirectly include this file:



Functions

• bool midipp::write_simple_drum_file (const std::string &filespec, const csvarray &csv)

Writes a csvarray object to a file in a simple INI format.

- bool midipp::write_sectioned_drum_file (const std::string &filespec, const csvarray &csv, bool writefooter)

 Writes a csvarray object to a drum file in a sectioned INI format.
- bool midipp::write_sectioned_patch_file (const std::string &filespec, const csvarray &csv, bool write-header)

Writes a csvarray object to a patch file in a sectioned INI format.

9.7.1 Detailed Description

Provides some free functions to write INI files, given a midipp::csvarray object.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-23

Last Edits 2014-05-08

Version

\$Revision\$ License \$XPC_SUITE_GPL_LICENSE\$

Provides a way to write various kinds of MIDI-related INI files.

Also provides some names and macros.

9.8 mainpage-reference.dox File Reference

This document describes the modules and functions of the libmidifilex library and the midicvt and midicvtpp applications.

9.8.1 Detailed Description

This document describes the modules and functions of the libmidifilex library and the midicvt and midicvtpp applications.

9.9 midi_functions.dox File Reference

This document describes the functions and parameters of the libmidifilex modules.

9.9.1 Detailed Description


This document describes the functions and parameters of the libmidifilex modules.

9.10 midicvt base.c File Reference

This module provides functions for basic MIDI/text conversions.

```
#include <ctype.h>
#include <malloc.h>
#include <errno.h>
#include <unistd.h>
#include <stdio.h>
#include <stdib.h>
#include <stdib.h>
#include <midicvt_base.h>
#include <midicvt_globals.h>
#include <midicvt_helpers.h>
#include <t2mf.h>
```

Include dependency graph for midicvt_base.c:



Macros

• #define MFILE_FORMAT_4 "MFile %d %d %d %d %d\n"

We now write out "MThd" instead of "MFile" for our generated results.

Functions

• static void checkchan (void)

Checks to make sure that yylex() == CH or yylex() == INT, and yyval >= 1 or yyval 16.

static void checkeol (void)

Check for the end-of-line.

· static void checknote (void)

Checks the incoming value from flex.

• static int fileputc (unsigned char c)

Callback function implementing Mf putc().

• static int filegetc (void)

Callback function implementing Mf_getc().

• static int getbyte (char *mess)

Gets the current byte value as contained in yyval.

• static int getint (char *mess)

Returns the current byte value as contained in yyval.

• static void get16val (void)

Question

• static int prs_error (char *s)

Outputs error messages to standard error.

static void syntax (void)

Calls psr_error() with a message of "Syntax error".

• void error (const char *s)

Writes an obvious error string to standard error.

static void prtime (void)

Writes the time of the current MIDI event to standard output in text format.

static void prtext (unsigned char *p, int leng)

Writes the provided text to standard output.

static void prhex (unsigned char *p, int leng)

Writes the provided text to standard output in hexadecimal format.

static char * prnote (int pitch)

Writes a note value to standard output.

static int my_header (int format, int ntrks, int division)

Callback function implementing Mf header().

static int my_trstart (void)

Callback function implementing Mf_starttrack().

• static int my_trend (long header_offset, unsigned long track_size)

Callback function implementing Mf_endtrack().

• static int my non (int chan, int pitch, int vol)

Callback function implementing Mf_on().

static int my_noff (int chan, int pitch, int vol)

Callback function implementing Mf_off().

static int my pressure (int chan, int pitch, int pressure)

Callback function implementing Mf pressure().

• static int my_parameter (int chan, int control, int value)

Callback function implementing Mf parameter().

• static int my_pitchbend (int chan, int lsb, int msb)

Callback function implementing Mf_pitchbend().

• static int my_program (int chan, int program)

Callback function implementing Mf_program().

• static int my_chanpressure (int chan, int pressure)

Callback function implementing Mf_chanpressure().

static int my sysex (int leng, char *mess)

 ${\it Callback\ function\ implementing\ Mf_sysex()}.$

• static int my mmisc (int typecode, int leng, char *mess)

Callback function implementing Mf_metamisc().

static int my_mspecial (int leng, char *mess)

Callback function implementing Mf sqspecific().

• static int my_mtext (int type, int leng, char *mess)

Callback function implementing Mf_text().

static int my_mseq (short int num)

Callback function implementing Mf_seqnum().

static int my meot (void)

Callback function implementing Mf_eot().

static int my_keysig (int sf, int mi)

Callback function implementing Mf_keysig().

static int my_tempo (long tempo)

Callback function implementing Mf tempo().

• static int my_timesig (int nn, int dd, int cc, int bb)

Callback function implementing Mf_timesig().

• static int my_smpte (int hr, int mn, int se, int fr, int ff)

Callback function implementing Mf_smpte().

static int my_arbitrary (int leng, char *mess)

Callback function implementing Mf_arbitrary().

static int my_error (const char *s)

Callback function implementing Mf_error().

static int my_writetrack (void)

Callback function implementing Mf_wtrack() and Mf_wtempotrack().

void midicvt_initfuncs_t2mf (void)

Makes the function assignments needed by the midifile library when converting a text file to MIDI.

void midicvt_initfuncs_mf2t (void)

Makes the function assignments needed by the midifile library when converting a MIDI file to text.

· void midicvt compile (void)

This function makes sure the "MFile" or (new) "MThd" token is found.

• static cbool_t redirect_stdout (const char *filename, const char *mode)

Redirects stdout to a file.

static cbool_t revert_stdout ()

Holds the file descriptor for stdout for later restoration.

cbool_t midicvt_setup_compile (void)

Sets up the incoming text file for compiling into MIDI.

• void midicvt_close_compile (void)

Closes the input file (yyin) and the output file (g_io_file) for the -compile option.

cbool_t midicvt_setup_mfread (void)

Sets up the file handles for both reading and writing.

void midicvt_close_mfread (void)

Checks g_io_file for an error status, closes this file handle if necessary, and restores stdout to norml if necessary.

Variables

• static unsigned char gs_data [5]

Holds up to four bytes of data that comprise the data values for a MIDI operation.

• static int gs_chan = 0

Holds the channel number of the MIDI channel currently being processed.

static int gs_saved_stdout = -1

Holds the file descriptor for stdout for later restoration.

static fpos_t gs_saved_stdout_pos

Holds the file position for stdout for later restoration.

9.10.1 Detailed Description

This module provides functions for basic MIDI/text conversions.

Library midicvt application

Author(s) Chris Ahlstrom and many other authors

Date 2014-04-09

Last Edits 2015-08-14

Version

\$Revision\$ License GNU GPL

Summary of MIDI messages:

We want to provide a very brief reference to the MIDI messages handled by the library and application in this project. Channel Voice Messages.

The first nybble is the message (e.g. note on), and the second nybble (denoted by "c") is the channel number.

One or more parameter bytes follow, and the first bit is 0, so that the values range from 0 to 127.

"kk" means "key" or note number, "vv" means "velocity" or some other "value", "pp" means "program" or "patch". Other variations are noted. All didits are hexadecimal.

- 8c kk vv. Note Off.
- 9c kk vv. Note On.
- Ac kk vv. Aftertouch (Polyphonic Key Pressure).
- Bc cc vv. Control (cc) Change.
- Cc pp . Program/patch (cc) Change.
- Dc pp . Aftertouch (Channel Pressure).
- Ec 11 mm. Pitch Wheel Change. Provides the least significant and most significant 14 bits.
- Fc mm . System Common Messages. See below.

System Common Messages:

```
- <code> F0 </code>. System Exclusive.
- <code> F1 </code>. Undefined.
- <code> F2 </code>. Song Position Pointer.
- <code> F3 </code>. Song Select.
- <code> F4 </code>. Undefined.
- <code> F5 </code>. Undefined.
- <code> F6 </code>. Tune Request.
- <code> F7 </code>. End-Of-Exclusive marker.
```

System Real-Time Messages:

```
<code> F8 </code>.
                      Timing Clock.
<code> F9 </code>.
                     Undefined.
                      Start.
<code> FA </code>.
<code> FB </code>.
                      Continue.
<code> FC </code>.
                      Stop.
<code> FD </code>.
                      Undefined.
<code> FE </code>.
                      Active Sensing.
<code> FF </code>.
                      Reset. In a MIDI file, this code is
                      used as an escape character to
                       introduce "meta events".
```

Meta Events:

"In" indicates the length byte. "tx" indicates all of the bytes that are part of the text of the meta-event. This text is ASCII in some cases, binary in the case of sequencer-specific data.

- FF 00 02 ss ss or FF 00 00. Sequence Number. Optional, but must occur at the beginning of an MTrk
- FF 01 ln tx . Text Event.
- FF 02 ln tx . Copyright Notice.

- FF 03 ln tx . Sequence/Track Name.
- FF 04 ln tx . Instrument Name.
- FF 05 ln tx . Lyric.
- FF 06 ln tx . Marker.
- FF 07 ln tx . Cue Point.
- FF 08 ln tx to FF 0F ln tx . Indeterminate/unrecognized text event.
- FF 20 01 cc . MIDI Channel Prefix.
- FF 2F 00 . End of Track.
- FF 51 03 tt tt tt. Set tempo.
- FF 54 05 hr mn se fr ff. SMPTE Offset.
- FF 58 04 nn dd cc bb. Time Signature.
- FF 59 02 sf mi . Key Signature.
- FF 7F ln tx . Sequencer-specific binary event.

That's all for now.

9.10.2 Macro Definition Documentation

9.10.2.1 #define MFILE_FORMAT_4 "MFile %d %d %d %d %d\n"

We now write out "MThd" instead of "MFile" for our generated results.

The reason? We were puzzled why we didn't see the header, after not having run this program for a long time.

Now, files that were written by the old (0.2) version of midicvt can still be read by the new version. One can write out the old tag using the -mfile option.

Definition at line 139 of file midicvt_base.c.

9.10.3 Function Documentation

9.10.3.1 static void checkchan (void) [static]

Checks to make sure that yylex() == CH or yylex() == INT, and yyval >= 1 or yyval 16.

Side-effect(s) The global variable gs_chan is set to yyval - 1.

Definition at line 1721 of file midicvt base.c.

9.10.3.2 void error (const char *s)

Writes an obvious error string to standard error.

Public Note that this is an public function used in other modules, and declared in the midicvt_base.h file.

Parameters

s Provides the null-terminated error message to be written.

Definition at line 177 of file midicvt_base.c.

```
9.10.3.3 static int filegetc ( void ) [static]
```

Callback function implementing Mf_getc().

This function increments the offset into the MIDI file, and then calls getc(g io file).

Returns

Returns the value returned by getc().

Definition at line 2068 of file midicvt_base.c.

```
9.10.3.4 static void get16val ( void ) [static]
```

Question

Does this function need to have and use a char pointer???

Definition at line 1827 of file midicvt base.c.

```
9.10.3.5 static int getbyte ( char * mess ) [static]
```

Gets the current byte value as contained in yyval.

Parameters

mess The message to print if yyval is greater than 127.

Returns

The value of yyval is returned. It is set to 0 if an error occurred.

Definition at line 1667 of file midicvt_base.c.

```
9.10.3.6 static int getint (char * mess) [static]
```

Returns the current byte value as contained in yyval.

Parameters

mess The message to print if yylex() is not equal to INT.

Returns

The value of yyval is returned. It is set to 0 if an error occurred.

Definition at line 1700 of file midicvt_base.c.

```
9.10.3.7 void midicvt_compile (void)
```

This function makes sure the "MFile" or (new) "MThd" token is found.

It then gathers up some status information and passes it to mfwrite().

Note

This function used to be called translate(), which was a bit ambiguous.

Definition at line 1629 of file midicvt base.c.

```
9.10.3.8 cbool t midicvt_setup_compile ( void )
```

Sets up the incoming text file for compiling into MIDI.

Returns

Returns true if all is well.

Definition at line 2167 of file midicvt_base.c.

9.10.3.9 cbool_t midicvt_setup_mfread (void)

Sets up the file handles for both reading and writing.

Returns

Returns true if all steps succeeded.

Definition at line 2231 of file midicvt_base.c.

```
9.10.3.10 static int my_arbitrary ( int leng, char * mess ) [static]
```

Callback function implementing Mf_arbitrary().

This function is called in readtrack() if there are additional bytes that are not part of a system exlusive continuation.

I have to confess that, right now, I don't know what that means.

This function writes the time, "Arb", followed by the message bytes, followed by the length. Why doesn't the length come first?

Parameters

leng	Provides the number of bytes in the message.
mess	Points to the bytes in the message.

Returns

Returns true, always.

Definition at line 1198 of file midicvt_base.c.

9.10.3.11 static int my_chanpressure (int chan, int pressure) [static]

Callback function implementing Mf_chanpressure().

Command: 0xDn .

A channel-pressure command has the following 3 bytes:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Channel-pressure byte. 0xDn .
- 3. Channel-pressure value byte. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
pressure	Provides the patch/program number to write.

Returns

Returns true, always.

Definition at line 766 of file midicvt_base.c.

9.10.3.12 static int my_error (const char * s) [static]

Callback function implementing Mf_error().

This function checks for garbage at the end of the MIDI file. If it does not find such garbage, then the error is simply printed.

Parameters

s Provides the error string to report.

Returns

Returns true, always.

Definition at line 1220 of file midicvt_base.c.

```
9.10.3.13 static int my_header ( int format, int ntrks, int division ) [static]
```

Callback function implementing Mf_header().

Provides a libmidifilex callback function to write the MIDI header data to standard output in text format.

This function is called by readheader() in midifilex.c, which reads:

- 1. "MThd" marker, 4 bytes, unterminated
- 2. Size (32-bits)
- 3. MIDI format (16-bits)
- 4. Number of tracks (16-bits)
- 5. Time division (16-bits)

and then calls this callback function, after which it flushes and additional bytes specified by the size parameter.

Parameters

format	Provides the byte describing the format of the MIDI file. This value will be 0, 1, or 2.
ntrks	Provides the byte describing the number of tracks in the MIDI file. This value ranges from 1
	to 65536. SMF 0 files will have only 1 track. SMF 1 has multiple tracks, with the first track
	containing song information.
division	Provides the time-division value. The first byte is either 0 (indicates the time format is ticks
	per quarter-note) or 1 (the time format is negative SMPTE). The second byte is the number
	of "ticks" per frame. For example, 0x80 indicates 128 ticks per frame.

Returns

Returns true, always.

Definition at line 440 of file midicvt_base.c.

```
9.10.3.14 static int my_keysig ( int sf, int mi ) [static]
```

Callback function implementing Mf_keysig().

This function prints "KeySig", followed by the sf parameter, followed by "major" or "minor", to standard output.

```
Command: FF 59 02 sf mi .
```

The format of this event is:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. End-of-track marker. 0x59 .
- 4. Length byte. 0x02 .
- 5. Data bytes:

- (a) sf = signature flats
 - -7: 7 flats
 - -1: 7 flat
 - 0: Key of C
 - 1: 1 sharp
 - 7: 7 sharps
- (b) mi = minor flag (0 = major; 1 = minor)

Parameters

sf	Provides the code for the keys above and below C. (I don't really understand what that mean,
	right now.)
mi	True (1) indicates the key is minor; otherwise it is major.

Returns

Returns true, always.

Definition at line 1039 of file midicvt base.c.

9.10.3.15 static int my_meot (void) [static]

Callback function implementing Mf_eot().

This function writes "Mata TrkEnd" to standard output.

Command: FF 00 .

The format of this event is:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. $0 \times FF$.
- 3. End-of-track marker. $0 \times 0F$.
- 4. Length byte. 0x00 .

There is no data for this command, so the length byte is 0.

Returns

Returns true, always.

Definition at line 997 of file midicvt_base.c.

9.10.3.16 static int my_mmisc (int typecode, int leng, char * mess) [static]

Callback function implementing Mf_metamisc().

This function prints "Meta", "0xnn" (the type of event), the length of the event as a byte, and then a stream of bytes, in hex format, to standard output.

Command: 0xFF .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Event-type byte. A 7-bit value, highest bit is 0. These range from 01 to 08 for the known text events. See the list of other values else where in this document.

- 4. Length byte.
- 5. Data bytes. Delimited by the length byte.

Parameters

typecode	Provides the type of meta event.
leng	Provides the number of bytes in the event.
mess	Provides a pointer to the event bytes.

Returns

Returns true, always.

Definition at line 841 of file midicvt base.c.

```
9.10.3.17 static int my_mseq( short int num ) [static]
```

Callback function implementing Mf_seqnum().

This function writes "SeqNr" and the sequence number to standard output.

Command: FF 00 02 .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Sequence-number marker. 0×00 .
- 4. Length byte. 0x02 .
- 5. Data bytes. Two bytes of data, I believe, at this time. As for ordering

Parameters

num	Provides the number to be converted to a sequence-number specification.

Returns

Returns true, always.

Definition at line 969 of file midicvt_base.c.

```
9.10.3.18 static int my_mspecial ( int leng, char * mess ) \texttt{[static]}
```

Callback function implementing Mf sqspecific().

This function prints "SeqSpec", the size of the event as a byte, and then a stream of bytes, in hex format, to standard output.

Command: 0xFF 0x7F ...

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Event-type byte. 0x7F .
- 4. Length byte.
- 5. Data bytes. Delimited by the length byte.

Parameters

leng	Provides the number of bytes in the event.
mess	Provides a pointer to the event bytes.

Returns

Returns true, always.

Definition at line 876 of file midicvt_base.c.

9.10.3.19 static int my_mtext (int type, int leng, char * mess) [static]

Callback function implementing Mf_text().

This function prints "SeqSpec", the size of the event as a byte, and then a stream of bytes, in hex format, to standard output.

Command: 0xFF .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Event-type byte. 0xnn.
- 4. Length byte.
- 5. Data bytes. Delimited by the length byte.

Parameters

type	Here, nn ranges from 01 to 0F. 01 to 08 are the known types of text event, while 09 to 0F are
	unrecognized text events. Other values are treat as in my_mmisc().
leng	Provides the number of bytes in the event.
mess	Provides a pointer to the event bytes.

Returns

Returns true, always.

Definition at line 916 of file midicvt_base.c.

9.10.3.20 static int my_noff (int chan, int pitch, int vol) [static]

Callback function implementing Mf_off().

Command: 0x8n .

Very similar to Note-On messages [see my_non()].

In our sample file, ex1.mid, there are no Note-Off messages, only Note-On messages with a velocity of 0.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.

_		
	vol	Provides the MIDI note velocity to write.

Returns

Returns true, always.

Definition at line 601 of file midicvt_base.c.

9.10.3.21 static int my_non (int chan, int pitch, int vol) [static]

Callback function implementing Mf on().

Command: 0x9n .

This function outputs the time using prtime(), then writes the channel, note, and velocity using the g_option_Onmsg format specifier.

The MIDI bytes for a note on message are 4 in number:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Note on byte. 0x9n . This byte is a status byte having two parts:
 - The first (most significant) nybble of this byte is 0x9.
 - The least significant nybble holds the channel number, ranging from 0x0 to 0xF. However, in our sample file, ex1.mid, there see to be notes in which the note-on byte is *missing*!!! This may be correlated to having a note velocity of 0, but not sure about that. There are no Note-Off messages in that file, by the way.
- 3. Note value byte. This value ranges from 0 to 127.
- 4. Note velocity byte. This value ranges from 0 to 127. It seems that a note off can be made by setting this value to zero. Again, not sure about that.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns true, always.

Definition at line 570 of file midicvt_base.c.

9.10.3.22 static int my_parameter (int chan, int control, int value) [static]

Callback function implementing Mf_parameter().

Command: 0xBn .

This function prints the Control Change message. This message has different parameters than the Note On/Off messages.

The MIDI bytes for a control-change message are 4 in number:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Control-change byte. 0xBn . This byte is a status byte having two parts, the command nybble and the channel nybble.
- 3. Control-change value byte. This value ranges from 0 to 127. It determines which controller (e.g. pitch or sustain) is changed.
- 4. Controller value byte. This value ranges from 0 to 127.

Parameters

ct	han	Provides the channel number to write.
con	trol	Provides the MIDI controller number to write.
va	lue	Provides the MIDI controller parameter value to write.

Returns

Returns true, always.

Definition at line 670 of file midicvt_base.c.

9.10.3.23 static int my_pitchbend (int chan, int lsb, int msb) [static]

Callback function implementing Mf_pitchbend().

Command: 0xEn .

- Ec 11 mm. Pitch Wheel Change. Provides the least significant and most significant 14 bits.
- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Pitch-bend byte. 0xEn .
- 3. Pitch, least-significat value byte. This value ranges from 0 to 127. It provides the lowest 7 bits of the pitch-bend parameter.
- 4. Pitch, most-significat value byte. It provides the highest 7 bits of the pitch-bend parameter.

Parameters

chan	Provides the channel number to write.
Isb	Provides the least-significant bits of the MIDI pitch-wheel value to write.
msb	Provides the most-significant bits of the MIDI pitch-wheel value to write.

Returns

Returns true, always.

Definition at line 708 of file midicvt_base.c.

9.10.3.24 static int my_pressure (int chan, int pitch, int pressure) [static]

Callback function implementing Mf_pressure().

Command: 0xAn .

Very similar to Note-On messages [see my_non()].

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
pressure	Provides the MIDI polyphonic key pressure value to write.

Returns

Returns true, always.

Definition at line 629 of file midicvt_base.c.

9.10.3.25 static int my_program (int chan, int program) [static]

Callback function implementing Mf_program().

Command: 0xCn .

A program-change (patch change) command has the following 3 bytes:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Program-change byte. 0xCn .
- 3. Program/patch number byte. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
program	Provides the patch/program number to write.

Returns

Returns true, always.

Definition at line 737 of file midicvt_base.c.

9.10.3.26 static int my_smpte (int hr, int mn, int se, int fr, int ff) [static]

Callback function implementing Mf_smpte().

Prints "SMPTE" and each of the parameters shown below, to standard output.

Parameters

hr	Provides the hour of the SMPTE time at which the track chunk is supposed to start. It should
	be present at the beginning of the track, before any non-zero delta times, and before any
	transmitable MIDI events.
mn	Provides the minutes of the SMPTE time.
se	Provides the seconds of the SMPTE time.
fr	Provides the frames of the SMPTE time.
ff	Provides the fractional frames of the SMPTE time, in 100ths of a frame, even in SMPTE-
	based tracks which specify as different frame subdivision for delta times

Returns

Returns true, always.

Definition at line 1169 of file midicvt_base.c.

9.10.3.27 static int my_sysex (int leng, char * mess) [static]

Callback function implementing Mf_sysex().

This function prints "SysEx" and then a stream of bytes, in hex format, to standard output.

Command: 0xF0 .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. System-exclusive byte. 0xF0 .
- 3. Manufacturer's code. A 7-bit value, highest bit is 0.
- 4. Data bytes. A series of 7-bit values.
- 5. EOS (End-of-System-exclusive) byte. $0\,\mathrm{xF}\,7$.

Parameters

leng	Provides the number of bytes in the message.
mess	Provides a pointer to the message bytes.

Returns

Returns true, always.

Definition at line 800 of file midicvt_base.c.

```
9.10.3.28 static int my_tempo ( long tempo ) [static]
```

Callback function implementing Mf_tempo().

Prints the string "Tempo" followed by the tempo value, to standard output.

Command: FF 51 03 tt tt tt.

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. End-of-track marker. 0x51 .
- 4. Length byte. 0×03 .
- 5. Data bytes. There are three data bytes that specify the tempo in "microseconds per MIDI quarter-note" or "24ths of a microsecond per MIDI clock". Chew on this conversion: 07 a1 20 == 500000 usec/quarter note == 1/2 second per quarter note == 120 bpm (beats per minute), where each quarter note is a beat.

Parameters

tempo	Provides the tempo value as a single integer.
-------	---

Returns

Returns true, always.

Definition at line 1078 of file midicvt_base.c.

9.10.3.29 static int my_timesig (int nn, int dd, int cc, int bb) [static]

Callback function implementing Mf_timesig().

Prints the string "TimeSig" followed by the four value needed for a key signature, to standard output.

Command: FF 58 04 nn dd cc bb.

As an example, this sequence of bytes:

FF 58 04 06 03 24 08

This is the complete event for 6/8 time, where the metronome clicks every three eighth-notes, but there are 24 clocks per quarter-note, 72 to the bar. That is, 6/8 time (8 is 2 to the 3rd power, so this is 06 03), 36 MIDI clocks per dotted-quarter (24 hex!), and eight notated 32nd-notes per quarter-note.

Parameters

nn	Provides the numerator of the time signature as it would be notated.
----	--

dd	Provides the denominator of the time signature as it would be notated. The denominator is a
	negative power of two, where 2 represents a quarter note, 3 represents an eighth note
СС	Provides the number of MIDI clock in a metronome click.
bb	The number of notated 32nd notes in a MIDI quarter-note (a MIDI quarter note is 24 MIDI
	clocks).

Returns

Returns true, always.

Definition at line 1123 of file midicvt base.c.

```
9.10.3.30 static int my_trend ( long header_offset, unsigned long track_size ) [static]
```

Callback function implementing Mf endtrack().

This function write "TrkEnd" and a newline to standard output, and decrements the global "tracks to do" counter.

In MIDI, the end-of-track marker is three bytes, ff 2f 00. One file has a 0a as well.

Parameters

header_offset	Offset of the header of the track that is now ending. This
track_size	Provides the actual size of the track. This parameter is not used in this callback.

Returns

Returns true, always.

Definition at line 508 of file midicvt_base.c.

```
9.10.3.31 static int my_trstart ( void ) [static]
```

Callback function implementing Mf starttrack().

This function writes "MTrk" and a newline to standard output and increments the global track number counter.

This marker is a 4-byte unterminated ASCII marker.

Returns

Returns true, always.

Definition at line 479 of file midicvt_base.c.

```
9.10.3.32 static int my_writetrack( void ) [static]
```

Callback function implementing Mf_wtrack() and Mf_wtempotrack().

This function is called for writing MIDI to text and for text to MIDI:

```
Mf_wtrack = my_writetrack;  // text-to-MIDI and vice versa
Mf_wtempotrack = my_writetrack;  // text-to-MIDI only

However, this function also <i> reads </i> data!!!
This function scans the return value of the flex function yylex()
until it finds it is equal to MTRK (which happens if the string
"MTrk" is found). A bunch of other markers ("TrkEnd", "SysEx",
"Meta", "Arb", and more (see t2mf.fl), are found and processed.

For writing MIDI, the following functions from the midifilex.c
module are called:
    - mf_w_midi_event(). Writes the "delta time", the MIDI event
```

```
type plus channel byte, plus the event data.,
- mf_w_sysex_event(). Writes the delta time and the SYSEX or
   "arbitrary" data for the event.
- mf_w_meta_event(). Writes the delta time and the meta-event.
There are a number of meta-events that are written.
```

Returns

Returns -1 upon an error, otherwise returns true (1).

Definition at line 1262 of file midicvt_base.c.

```
9.10.3.33 static void prhex (unsigned char *p, int leng) [static]
```

Writes the provided text to standard output in hexadecimal format.

It also handles the -fold option.

Parameters

р	Provides the characters to be written.
leng	Provides the number of characters to be written.

Definition at line 339 of file midicvt_base.c.

```
9.10.3.34 static char* prnote (int pitch) [static]
```

Writes a note value to standard output.

If the –verbose option was given, then the note is written as a letter value with the octave number following it. Otherwise, the note is written as a integer MIDI note value.

Note

Not sure why this function isn't called "prnote()", so I renamed it from "mknote()".

Not threadsafe Due to the static buffer buf[8] used inside this function.

Parameters

pitch	Provides the MIDI note value to be written.

Returns

Returns a pointer to the beginning of the static buffer buf[].

Definition at line 387 of file midicvt base.c.

```
9.10.3.35 static int prs_error ( char * s ) [static]
```

Outputs error messages to standard error.

This function also skips thto the end of the line of the input. If the end-of-file is encountered, then exit(1) is called. If there is an error status, then a longjmp() to g_status_erjump is called.

Parameters

s	Provides the error string. Note that yyleng and yytext are global inputs to this function, as
	well.

Returns

Returns true, always.

Definition at line 1585 of file midicvt_base.c.

```
9.10.3.36 static void prtext (unsigned char * p, int leng) [static]
```

Writes the provided text to standard output.

The text is enclosed in quotes, and the backslash escape character is emitted where needed.

This function will also employ the -fold option.

Parameters

р	Provides the characters to be written. It is unsigned, but the characters should all, I think, be straight 7-bit ASCII printing characters.
leng	Provides the number of characters to be written.

Definition at line 265 of file midicvt_base.c.

```
9.10.3.37 static void prtime( void ) [static]
```

Writes the time of the current MIDI event to standard output in text format.

This function handles the "absolute times" (-time) and "verbose notes" (-verbose) options as well.

Definition at line 215 of file midicvt_base.c.

```
9.10.3.38 static cbool_t redirect_stdout ( const char * filename, const char * mode ) [static]
```

Redirects stdout to a file.

Parameters

filena	ame	Provides the filename to be use for the out that would have gone to stdout.
m	ode	Provides the mode to use on the file. Probably makes sense only in Windows, which this
		application doesn't support yet. Should be either "w" or "wb", but this is not verified. You're a big boy.

Returns

Returns true (1) if the setup succeeded. Do not rely on using stdout in the rest of the program if this function returns false (0).


Definition at line 2092 of file midicvt base.c.

9.11 midicvt_base.h File Reference


This module provides functions for a basic MIDI/text conversion application.

```
#include <stdio.h>
#include <midicvt_macros.h>
#include <midifilex.h>
```

Include dependency graph for midicvt_base.h:



This graph shows which files directly or indirectly include this file:



Functions

void error (const char *s)

Writes an obvious error string to standard error.

void midicvt_initfuncs_t2mf (void)

Makes the function assignments needed by the midifile library when converting a text file to MIDI.

void midicvt_initfuncs_mf2t (void)

Makes the function assignments needed by the midifile library when converting a MIDI file to text.

cbool_t midicvt_setup_compile (void)

Sets up the incoming text file for compiling into MIDI.

void midicvt_close_compile (void)

Closes the input file (yyin) and the output file (g_io_file) for the –compile option.

void midicvt_compile (void)

This function makes sure the "MFile" or (new) "MThd" token is found.

cbool_t midicvt_setup_mfread (void)

Sets up the file handles for both reading and writing.

void midicvt_close_mfread (void)

Checks g_io_file for an error status, closes this file handle if necessary, and restores stdout to norml if necessary.

9.11.1 Detailed Description

This module provides functions for a basic MIDI/text conversion application.

Library midicvt application portion of libmidifilex

Author(s) Chris Ahlstrom and many others; see documentation

Date 2014-04-09

Last Edits 2014-05-20

Version

\$Revision\$ License GNU GPL

9.11.2 Function Documentation

9.11.2.1 void error (const char *s)

Writes an obvious error string to standard error.

Public Note that this is an public function used in other modules, and declared in the midicvt_base.h file.

Parameters

s Provides the null-terminated error message to be written.

Definition at line 177 of file midicvt base.c.

9.11.2.2 void midicvt_compile (void)

This function makes sure the "MFile" or (new) "MThd" token is found.

It then gathers up some status information and passes it to mfwrite().

Note

This function used to be called translate(), which was a bit ambiguous.

Definition at line 1629 of file midicvt_base.c.

9.11.2.3 cbool_t midicvt_setup_compile (void)

Sets up the incoming text file for compiling into MIDI.

Returns

Returns true if all is well.

Definition at line 2167 of file midicvt_base.c.

9.11.2.4 cbool_t midicvt_setup_mfread (void)

Sets up the file handles for both reading and writing.

Returns

Returns true if all steps succeeded.


Definition at line 2231 of file midicvt_base.c.

9.12 midicvt_globals.c File Reference

This module provides a place to collect all the global variables used, and functions to set them.

```
#include <midicvt_macros.h>
#include <midicvt_globals.h>
#include <midicvt_helpers.h>
#include <t2mf.h>
```

Include dependency graph for midicvt_globals.c:



Functions

void midicvt_set_defaults (void)

Sets some defaults for status variables.

void midicvt_set_option_fold (int f)

'Setter' function for member g_option_fold

int midicvt_option_fold (void)

'Getter' function for member g_option_fold

void midicvt_set_option_mfile (cbool_t f)

'Setter' function for member g_option_mfile_tag

cbool_t midicvt_option_mfile (void)

 ${\it 'Getter' function for member g_option_mfile_tag}$

void midicvt_set_option_strict (cbool_t f)

'Setter' function for member g_option_strict_track

cbool t midicvt option strict (void)

'Getter' function for member g_option_strict_track

void midicvt_set_option_ignore (cbool_t f)

'Setter' function for member g_option_ignore_track

cbool_t midicvt_option_ignore (void)

 ${\it 'Getter' function for member g_option_ignore_track}$

void midicvt_set_option_verbose (cbool_t f)

'Setter' function for member g_option_verbose

cbool_t midicvt_option_verbose (void)

'Getter' function for member g_option_verbose

void midicvt_set_option_verbose_notes (cbool_t f)

'Setter' function for member g_option_verbose_notes

cbool_t midicvt_option_verbose_notes (void)

'Getter' function for member g_option_verbose_notes

void midicvt_set_option_absolute_times (cbool_t f)

'Setter' function for member g_option_absolute_times

cbool_t midicvt_option_absolute_times (void)

'Getter' function for member g_option_absolute_times

void midicvt_set_option_debug (cbool_t f)

'Setter' function for member g_option_debug

· cbool t midicvt option debug (void)

'Getter' function for member g_option_debug

void midicvt_set_option_compile (cbool_t f)

'Setter' function for member g_option_docompile

cbool_t midicvt_option_compile (void)

'Getter' function for member g_option_docompile

void midicvt_set_option_m2m (cbool_t f)

'Setter' function for member g_option_midi2midi

cbool t midicvt option m2m (void)

'Getter' function for member g_option_midi2midi

Variables

FILE * g_io_file = nullptr

Global variables!

long yyval = 0UL

Use externs from an include file! The flex-generated code is a bit messy.

9.12.1 Detailed Description

This module provides a place to collect all the global variables used, and functions to set them.

Library midicvt application

Author(s) Chris Ahlstrom

Date 2014-04-09

Last Edits 2015-08-19

Version

\$Revision\$ License GNU GPL

9.12.2 Function Documentation

9.12.2.1 cbool_t midicvt_option_compile (void)

'Getter' function for member g_option_docompile

We need to expose this value for main() to use.

Definition at line 308 of file midicvt_globals.c.

```
9.12.2.2 cbool_t midicvt_option_m2m ( void )
```

'Getter' function for member g_option_midi2midi

We need to expose this value for main() to use.

Definition at line 330 of file midicvt_globals.c.

9.12.3 Variable Documentation

9.12.3.1 long yyval = 0UL

Use externs from an include file! The flex-generated code is a bit messy.


The generated t2mflex.c file defines these variables, we declare them in t2fm.h, and have to define yyval here. Bleh. Definition at line 89 of file midicvt_globals.c.

9.13 midicvt_globals.h File Reference


This module provides global variables and accessor functions for the midicvt portion of libmidifilex.

```
#include <setjmp.h>
#include <stdio.h>
#include <midicvt_macros.h>
```

Include dependency graph for midicvt globals.h:



This graph shows which files directly or indirectly include this file:



Macros

#define READMT_EOF EOF

Provides a return value for readmt() that indicates that EOF was encountered.

• #define READMT_IGNORE_NON_MTRK (-9)

Provides a return value for readmt() that indicates that "MTrk" was not matched, but we're simply ignoring such results.

Functions

void midicvt set defaults (void)

Sets some defaults for status variables.

void midicvt_set_option_fold (int f)

'Setter' function for member g option fold

int midicvt_option_fold (void)

'Getter' function for member g_option_fold

void midicvt_set_option_mfile (cbool_t f)

'Setter' function for member g_option_mfile_tag

cbool_t midicvt_option_mfile (void)

'Getter' function for member g option mfile tag

void midicvt_set_option_strict (cbool_t f)

'Setter' function for member g_option_strict_track

cbool_t midicvt_option_strict (void)

'Getter' function for member g_option_strict_track

void midicvt_set_option_ignore (cbool_t f)

'Setter' function for member g_option_ignore_track

cbool_t midicvt_option_ignore (void)

'Getter' function for member g_option_ignore_track

void midicvt_set_option_verbose (cbool_t f)

'Setter' function for member g_option_verbose

· cbool_t midicvt_option_verbose (void)

'Getter' function for member g option verbose

void midicvt_set_option_verbose_notes (cbool_t f)

'Setter' function for member g_option_verbose_notes

cbool_t midicvt_option_verbose_notes (void)

'Getter' function for member g_option_verbose_notes

void midicvt_set_option_absolute_times (cbool_t f)

'Setter' function for member g_option_absolute_times

• cbool_t midicvt_option_absolute_times (void)

'Getter' function for member g_option_absolute_times

void midicvt_set_option_debug (cbool_t f)

'Setter' function for member g_option_debug

cbool_t midicvt_option_debug (void)

'Getter' function for member g_option_debug

void midicvt_set_option_compile (cbool_t f)

'Setter' function for member a option docompile

cbool_t midicvt_option_compile (void)

'Getter' function for member g_option_docompile

void midicvt_set_option_m2m (cbool_t f)

'Setter' function for member g_option_midi2midi

· cbool_t midicvt_option_m2m (void)

'Getter' function for member g_option_midi2midi

Variables

• FILE * g_io_file

Global variables!

long yyval

Use externs from an include file! The flex-generated code is a bit messy.

9.13.1 Detailed Description

This module provides global variables and accessor functions for the midicvt portion of libmidifilex.

Library midicvt application portion of libmidifilex

Author(s) Chris Ahlstrom and others; see documentation

Date 2014-04-09

Last Edits 2015-08-19

Version

\$Revision\$ License GNU GPL

9.13.2 Macro Definition Documentation

```
9.13.2.1 #define READMT_EOF EOF
```

Provides a return value for readmt() that indicates that EOF was encountered.

This is a more searchable macro for EOF.

Definition at line 49 of file midicvt_globals.h.

```
9.13.3 Function Documentation
```

```
9.13.3.1 cbool_t midicvt_option_compile ( void )
```

'Getter' function for member g_option_docompile

We need to expose this value for main() to use.

Definition at line 308 of file midicvt_globals.c.

```
9.13.3.2 cbool_t midicvt_option_m2m ( void )
```

'Getter' function for member g_option_midi2midi

We need to expose this value for main() to use.

Definition at line 330 of file midicvt_globals.c.

9.13.4 Variable Documentation

9.13.4.1 long yyval

Use externs from an include file! The flex-generated code is a bit messy.

The generated t2mflex.c file defines these variables, we declare them in t2fm.h, and have to define yyval here. Bleh.


Definition at line 89 of file midicvt_globals.c.

9.14 midicvt_helpers.c File Reference

This module provides the help text for midicvt.

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <midifilex.h>
#include <midicvt_globals.h>
#include <midicvt_helpers.h>
```

Include dependency graph for midicvt_helpers.c:



Macros

#define MIDICVT_PATH_MAX 1024

Maximum path-name length.

Functions

void midicvt_version (const char *version)

Provides the version text for the midicvt-related programs.

void midicvt_help (const char *version)

Provides the help text for the midicvt program.

· cbool_t midicvt_have_input_file ()

'Getter' function for member gs_have_input_file Provides a safe accessor for this global variable.

• const char * midicvt_input_file ()

'Getter' function for member gs_input_file Provides a safe accessor for this global variable.

cbool_t midicvt_set_input_file (const char *inputfile)

Sets the input file-name.

· cbool_t midicvt_have_output_file ()

'Getter' function for member gs_have_output_file Safe accessor.

const char * midicvt_output_file ()

'Getter' function for member gs_output_file Safe accessor.

cbool_t midicvt_set_output_file (const char *outputfile)

Sets the output file-name.

• long midi_file_offset (void)

Exposes the file-offset counter, useful in debugging.

• void midi_file_offset_clear (void)

Exposes the file-offset counter, useful in debugging.

void midi file offset increment (void)

Increments the file-offset counter.

static int report (const char *msg)

Provides an optional and simple reporting function to be used by libmidifile.

cbool_t check_option (const char *source, const char *shortopt, const char *longopt)

Checks the option argument to see if it matches a short or a long option.

cbool_t midicvt_parse (int argc, char *argv[], const char *version)

Parses the midicvt (C) command line.

Variables

static const char *const gs_help_version = "midicvt v 0.2"

Default version string.

static const char *const gs_help_usage_1

Help string.

• static cbool_t gs_have_input_file = false

Indicates if an input file has yet been specified on the command line.

static char gs_input_file [MIDICVT_PATH_MAX]

Holds the value of the input file name.

• static cbool_t gs_have_output_file = false

Indicates if an output file has yet been specified on the command line.

• static char gs_output_file [MIDICVT_PATH_MAX]

Holds the value of the output file name.

static long gs_file_offset = 0

Provides the current offset into the global input file.

9.14.1 Detailed Description

This module provides the help text for midicvt.

Library midicvt application

Author(s) Chris Ahlstrom

Date 2014-04-19

Last Edits 2015-08-19

Version

\$Revision\$ License GNU GPL

We've offloaded the help text of midicvt to this module so that it can be re-used in an upcoming C++ version of midicvt.

Also for code re-use, the flex and file-access code from main() have been moved to this module.

9.14.2 Macro Definition Documentation

9.14.2.1 #define MIDICVT PATH MAX 1024

Maximum path-name length.

(We don't really support Windows yet.)

Definition at line 132 of file midicvt_helpers.c.

9.14.3 Function Documentation

9.14.3.1 cbool_t check_option (const char * source, const char * shortopt, const char * longopt)

Checks the option argument to see if it matches a short or a long option.

None of these values are checked for being null, since they are hardwired in the code, and the programmer will fix them to make the program work. :-D

Parameters

source	Provides the source argument, taken from the command line. If empty, the check will fail.
shortopt	Provides the short version of the option, such as "-c". If empty, this value is ignored.
longopt	Provides the long version of the option, such as "compile". If empty, this value is ignored.

Definition at line 393 of file midicvt_helpers.c.

9.14.3.2 long midi_file_offset (void)

Exposes the file-offset counter, useful in debugging.

Since this value is used in reporting on the character just gotten, and the offset is already incremented at that point, we deduct one from the offset.

Definition at line 319 of file midicvt_helpers.c.

9.14.3.3 void midicvt_help (const char * version)

Provides the help text for the midicvt program.

Parameters

version	Provides the optional version information.

Definition at line 196 of file midicvt_helpers.c.

9.14.3.4 cbool_t midicvt_parse (int argc, char * argv[], const char * version)

Parses the midicvt (C) command line.

Parameters

argc	Provides the command-line argument count, including the name of the program.
argv	Provides the command-line argument list, including the name of the program.
version	Provides the actual version string for the -version and -help options to display.

Returns

Returns true if there was no "--help" or "--version" option, and the other options were legal options for the midicvt program.

Definition at line 431 of file midicvt_helpers.c.

9.14.3.5 cbool_t midicvt_set_input_file (const char * inputfile)

Sets the input file-name.

Parameters

inputfile	Provides the full path specification for the input file.

Returns

Returns true if the file-name was valid and able to fit in the file-name buffer.

Definition at line 241 of file midicvt helpers.c.

9.14.3.6 cbool_t midicvt_set_output_file (const char * outputfile)

Sets the output file-name.

Parameters

|--|

Returns

Returns true if the file-name was valid and able to fit in the file-name buffer.

Definition at line 293 of file midicvt_helpers.c.

```
9.14.3.7 void midicvt_version ( const char * version )
```

Provides the version text for the midicvt-related programs.

Parameters

version	Provides the optional version information.
---------	--

Definition at line 180 of file midicvt helpers.c.

```
9.14.3.8 static int report (const char * msg ) [static]
```

Provides an optional and simple reporting function to be used by libmidifile.

Parameters

msg Provides the basic message to be written to standard error.

Returns

Returns 1 if the result of midi file offset() is greater-than-or-equal to 0, and it returns 0 otherwise.

Definition at line 357 of file midicvt_helpers.c.

9.14.4 Variable Documentation

```
9.14.4.1 cbool_t gs_have_input_file = false [static]
```

Indicates if an input file has yet been specified on the command line.

This value is usually the first non-option argument specified, or the parameter for the -i (-input) or -c (-compile) options.

Definition at line 142 of file midicvt_helpers.c.

```
9.14.4.2 cbool t gs_have_output_file = false [static]
```

Indicates if an output file has yet been specified on the command line.

This value is usually the second non-option argument specified, or the parameter for the -o (-output) option.

Definition at line 157 of file midicvt_helpers.c.

```
9.14.4.3 const char* const gs_help_usage_1 [static]
```

Initial value:

```
"\n"
"midicvt refactors the midicomp program for translating between MIDI/SMF and\n"
"text files. Compare it to the midi2text project at code.google.com.\n"
"\n"
"Command line argument usage:\n"
```

Help string.

Because of legacy C rules, we have to define 5 different help strings to avail ourselves of enough characters.

Definition at line 61 of file midicvt helpers.c.

9.14.4.4 const char* const gs_help_version = "midicvt v 0.2" [static]

Default version string.

Normally, the caller of midicvt_version() will provide a string, though.

Definition at line 54 of file midicvt_helpers.c.

9.14.4.5 char gs_input_file[MIDICVT_PATH_MAX] [static]

Holds the value of the input file name.

Restricted to 1024 bytes for now, but we should make it a heap variable soon.

Definition at line 149 of file midicvt_helpers.c.

9.14.4.6 char gs_output_file[MIDICVT_PATH_MAX] [static]

Holds the value of the output file name.

Restricted to 1024 bytes for now, but we should make it a heap variable soon.

Definition at line 164 of file midicvt_helpers.c.

9.15 midicvt_helpers.h File Reference


This module declares the help and version functions for midicvt.

#include <midicvt_macros.h>
Include dependency graph for midicvt_helpers.h:

midicvt_helpers.h

midicvt macros.h

This graph shows which files directly or indirectly include this file:



Functions

cbool t check option (const char *source, const char *shortopt, const char *longopt)

Checks the option argument to see if it matches a short or a long option.

void midicvt version (const char *version)

Provides the version text for the midicvt-related programs.

void midicvt_help (const char *version)

Provides the help text for the midicvt program.

cbool_t midicvt_set_input_file (const char *inputfile)

Sets the input file-name.

• cbool_t midicvt_have_input_file ()

'Getter' function for member gs_have_input_file Provides a safe accessor for this global variable.

const char * midicvt_input_file ()

'Getter' function for member gs_input_file Provides a safe accessor for this global variable.

• cbool_t midicvt_set_output_file (const char *outputfile)

Sets the output file-name.

· cbool t midicvt have output file ()

'Getter' function for member gs_have_output_file Safe accessor.

const char * midicvt_output_file ()

'Getter' function for member gs_output_file Safe accessor.

cbool t midicvt parse (int argc, char *argv[], const char *version)

Parses the midicvt (C) command line.

long midi file offset (void)

Exposes the file-offset counter, useful in debugging.

void midi_file_offset_clear (void)

Exposes the file-offset counter, useful in debugging.

void midi_file_offset_increment (void)

Increments the file-offset counter.

9.15.1 Detailed Description

This module declares the help and version functions for midicvt.

Library midicvt application

Author(s) Chris Ahlstrom

Date 2014-04-19

Last Edits 2014-04-23

Version

\$Revision\$ License GNU GPL

We've offloaded the help text of midicvt to this module so that it can be re-used in an upcoming C++ version of midicvt.

```
9.15.2 Function Documentation
```

9.15.2.1 cbool_t check_option (const char * source, const char * shortopt, const char * longopt)

Checks the option argument to see if it matches a short or a long option.

None of these values are checked for being null, since they are hardwired in the code, and the programmer will fix them to make the program work. :-D

Parameters

source	Provides the source argument, taken from the command line. If empty, the check will fail.
shortopt	Provides the short version of the option, such as "-c". If empty, this value is ignored.
longopt	Provides the long version of the option, such as "compile". If empty, this value is ignored.

Definition at line 393 of file midicvt_helpers.c.

9.15.2.2 long midi_file_offset (void)

Exposes the file-offset counter, useful in debugging.

Since this value is used in reporting on the character just gotten, and the offset is already incremented at that point, we deduct one from the offset.

Definition at line 319 of file midicvt_helpers.c.

9.15.2.3 void midicvt_help (const char * version)

Provides the help text for the midicvt program.

Parameters

version	Provides the optional version information.
---------	--

Definition at line 196 of file midicvt_helpers.c.

9.15.2.4 cbool_t midicvt_parse (int argc, char * argv[], const char * version)

Parses the midicvt (C) command line.

Parameters

argc	Provides the command-line argument count, including the name of the program.
argv	Provides the command-line argument list, including the name of the program.
version	Provides the actual version string for the -version and -help options to display.

Returns

Returns true if there was no "--help" or "--version" option, and the other options were legal options for the midicvt program.

Definition at line 431 of file midicvt_helpers.c.

9.15.2.5 cbool_t midicvt_set_input_file (const char * inputfile)

Sets the input file-name.

Parameters

inputfile	Provides the full path specification for the input file.

Returns

Returns true if the file-name was valid and able to fit in the file-name buffer.

Definition at line 241 of file midicvt_helpers.c.

9.15.2.6 cbool_t midicvt_set_output_file (const char * outputfile)

Sets the output file-name.

Parameters

outputfile	Provides the full path specification for the output file.

Returns

Returns true if the file-name was valid and able to fit in the file-name buffer.

Definition at line 293 of file midicvt_helpers.c.

```
9.15.2.7 void midicvt_version ( const char * version )
```

Provides the version text for the midicvt-related programs.

Parameters

version	Provides the optional version information.

Definition at line 180 of file midicvt_helpers.c.

9.16 midicvt_license.dox File Reference

This file is a copy of the main license file.

9.16.1 Detailed Description


This file is a copy of the main license file.

9.17 midicvt_m2m.c File Reference

This module provides functions for basic MIDI-to-MIDI conversions.

```
#include <ctype.h>
#include <malloc.h>
#include <errno.h>
#include <unistd.h>
#include <stdio.h>
#include <stdib.h>
#include <stdib.h>
#include <midicvt_macros.h>
#include <midicvt_m2m.h>
#include <midicvt_globals.h>
#include <midicvt_helpers.h>
#include <midicvt_helpers.h>
#include <midifilex.h>
```

Include dependency graph for midicvt_m2m.c:



Functions

static int fileputc (unsigned char c)

Callback function implementing Mf_putc() for MIDI-to-MIDI conversions.

static int filegetc (void)

Callback function implementing Mf_getc().

static int m2m error (const char *s)

Callback function implementing Mf_error().

• static int m2m header (int format, int ntrks, int division)

Callback function implementing Mf_header().

static int m2m_trstart (void)

Callback function implementing Mf_starttrack().

• static int m2m trend (long header offset, unsigned long track size)

Callback function implementing Mf_endtrack().

• int m2m_non (int chan, int pitch, int vol)

Callback function implementing Mf on().

int m2m_noff (int chan, int pitch, int vol)

Callback function implementing Mf_off().

• int m2m_pressure (int chan, int pitch, int pressure)

Callback function implementing Mf_pressure().

• int m2m parameter (int chan, int control, int value)

Callback function implementing Mf parameter().

• int m2m_pitchbend (int chan, int lsb, int msb)

Callback function implementing Mf_pitchbend().

int m2m_program (int chan, int program)

Callback function implementing Mf_program().

• int m2m_chanpressure (int chan, int pressure)

Callback function implementing Mf_chanpressure().

• static int m2m_sysex (int leng, char *mess)

Callback function implementing Mf sysex().

• static int m2m_mmisc (int typecode, int leng, char *mess)

Callback function implementing Mf_metamisc().

• static int m2m_mspecial (int leng, char *mess)

Callback function implementing Mf_sqspecific().

static int m2m_mtext (int type, int leng, char *mess)

Callback function implementing Mf text().

• static int m2m_mseq (short int num)

Callback function implementing Mf_seqnum().

int m2m_meot (void)

Callback function implementing Mf_eot().

static int m2m_keysig (int sf, int mi)

 ${\it Callback function implementing Mf_keysig()}.$

static int m2m_tempo (long tempo)

 ${\it Callback\ function\ implementing\ Mf_tempo()}.$

• static int m2m_timesig (int nn, int dd, int cc, int bb)

Callback function implementing Mf_timesig().

• static int m2m smpte (int hr, int mn, int se, int fr, int ff)

Callback function implementing Mf_smpte().

static int m2m_arbitrary (int leng, char *mess)

Callback function implementing Mf arbitrary().

void midicvt_initfuncs_m2m (void)

Makes the function assignments needed by the midifile library when converting a MIDI file to text.

9.17.1 Detailed Description

This module provides functions for basic MIDI-to-MIDI conversions.

Library midicvt application

Author(s) Chris Ahlstrom and many other authors

Date 2014-04-27

Last Edits 2014-05-20

Version

\$Revision\$ License GNU GPL

Why do we want to convert MIDI-to-MIDI? Well, for one thing, as we have seen with some of the test files, that conversion can fix MIDI files.

For another thing, we can insert transformations directly into the midicvt program, and call the functions here to write out the transformed MIDI. This work will give users some stock functionality without having to dealing with pipes and scripts.

A program that transforms MIDI data will define a callback function that first transforms the MIDI data, and then calls one of the functions here to write the MIDI.

9.17.2 Function Documentation

```
9.17.2.1 static int filegetc ( void ) [static]
```

Callback function implementing Mf_getc().

This function reads from the g io file FILE pointer.

Returns

Returns the value returned by getc(), or a -1 upon error.

Definition at line 99 of file midicvt_m2m.c.

```
9.17.2.2 static int fileputc (unsigned char c) [static]
```

Callback function implementing Mf_putc() for MIDI-to-MIDI conversions.

This function writes to the g_redirect_file FILE pointer.

Parameters

c Provides the character to be written.

Returns

Returns the value returned by putc(), or a -1 upon error.

Definition at line 77 of file midicvt m2m.c.

```
9.17.2.3 static int m2m_arbitrary (int leng, char * mess ) [static]
```

Callback function implementing Mf_arbitrary().

This function is called in readtrack() if there are additional bytes that are not part of a system exlusive continuation.

I have to confess that, right now, I don't know what that means.

Parameters

leng	Provides the number of bytes in the message.
mess	Points to the bytes in the message.

Returns

Returns true, always.

Definition at line 991 of file midicvt_m2m.c.

9.17.2.4 int m2m_chanpressure (int chan, int pressure)

Callback function implementing Mf_chanpressure().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xDn .

A channel-pressure command has the following 3 bytes:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Channel-pressure byte. 0xDn .
- 3. Channel-pressure value byte. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
pressure	Provides the patch/program number to write.

Returns

Returns true, always.

Definition at line 561 of file midicvt_m2m.c.

9.17.2.5 static int m2m_error (const char *s) [static]

Callback function implementing Mf_error().

This fuction checks for garbage at the end of the MIDI file. If it does not find such garbage, then the error is simply printed.

Parameters

s	Provides the error string to report.

Returns

Returns true, always.

Definition at line 128 of file midicvt_m2m.c.

9.17.2.6 static int m2m_header (int format, int ntrks, int division) [static]

Callback function implementing Mf_header().

Provides a libmidifilex callback function to write the MIDI header data to standard output in MIDI format.

This function is called by readheader() in the midifilex.c module. It merely needs to pass the parameters to the mf_w_header_chunk() function defined in that module.

Parameters

forma	t Provides the byte describing the format (0, 1, or 2) of the MIDI file.
ntrk	Provides the byte describing the number of tracks in the MIDI file. This value ranges from 1
	to 65536. SMF 0 files have 1 track, SMF 1 has multiple tracks, with the first track containing
	song information.
divisio	Provides the time-division value. The first byte is either 0 (indicates the time format is ticks
	per quarter-note) or 1 (the time format is negative SMPTE). The second byte is the number
	of "ticks" per frame. For example, 0x80 indicates 128 ticks per frame.

Returns

Returns true, always.

Definition at line 168 of file midicvt_m2m.c.

9.17.2.7 static int m2m_keysig (int sf, int mi) [static]

Callback function implementing Mf_keysig().

This function prints "KeySig", followed by the sf parameter, followed by "major" or "minor", to standard output.

Command: FF 59 02 sf mi .

The format of this event is:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. End-of-track marker. 0x59 .
- 4. Length byte. 0x02 .
- 5. Data bytes:
 - (a) sf = signature flats
 - -7: 7 flats
 - -1: 7 flat
 - 0: Key of C
 - 1: 1 sharp
 - 7: 7 sharps
 - (b) mi = minor flag (0 = major; 1 = minor)

Parameters

sf	Provides the code for the keys above and below C. (I don't really understand what that mean,
	right now.)
mi	True (1) indicates the key is minor; otherwise it is major.

Returns

Returns true, always.

Definition at line 835 of file midicvt_m2m.c.

9.17.2.8 int m2m_meot (void)

Callback function implementing Mf_eot().

This function writes "Mata TrkEnd" to standard output. However the m2m_trend() function takes care of this for the MIDI-to-MIDI conversion.

So this function is unused; we make it non-static (but don't expose it in the header file) just to avoid a compiler warning.

Command: FF 00 .

The format of this event is:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. End-of-track marker. $0 \times 0F$.
- 4. Length byte. 0×00 .

There is no data for this command, so the length byte is 0.

Returns

Returns true, always.

Definition at line 792 of file midicvt_m2m.c.

9.17.2.9 static int m2m_mmisc (int typecode, int leng, char * mess) [static]

Callback function implementing Mf_metamisc().

This function prints "Meta", "0xnn" (the type of event), the length of the event as a byte, and then a stream of bytes, in hex format, to standard output.

Command: 0xFF .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Event-type byte. A 7-bit value, highest bit is 0. These range from 01 to 08 for the known text events. See the list of other values else where in this document.
- 4. Length byte.
- 5. Data bytes. Delimited by the length byte.

Parameters

typecode	Provides the type of meta event.
leng	Provides the number of bytes in the event.
mess	Provides a pointer to the event bytes.

Returns

Returns true, always.

Definition at line 635 of file midicvt_m2m.c.

```
9.17.2.10 static int m2m_mseq ( short int num ) [static]
```

Callback function implementing Mf_seqnum().

This function writes "SeqNr" and the sequence number to standard output.

```
Command: FF 00 02 ss ss or FF 00 00.
```

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Sequence-number marker. 0x00 .
- 4. Length byte. 0×02 .
- 5. Data bytes. Two byte of data, I believe, at this time.

Todo Need to figure out the portable format of the sequence number bytes.

Returns

Returns true, always.

Definition at line 747 of file midicvt_m2m.c.

```
9.17.2.11 static int m2m_mspecial (int leng, char * mess) [static]
```

Callback function implementing Mf sqspecific().

This function prints "SeqSpec", the size of the event as a byte, and then a stream of bytes, in hex format, to standard output.

```
Command: 0xFF 0x7F ...
```

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Event-type byte. $0 \times 7F$.
- 4. Length byte.
- 5. Data bytes. Delimited by the length byte.

Parameters

leng	Provides the number of bytes in the event.
mess	Provides a pointer to the event bytes.

Returns

Returns true, always.

Definition at line 671 of file midicvt_m2m.c.

9.17.2.12 static int m2m_mtext (int type, int leng, char * mess) [static]

Callback function implementing Mf_text().

This function prints "SeqSpec", the size of the event as a byte, and then a stream of bytes, in hex format, to standard output.

Command: 0xFF .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. Event-type byte. 0xnn.
- 4. Length byte.
- 5. Data bytes. Delimited by the length byte.

(void) mf_w_meta_event(Mf_currtime, text_event, mess, (long) leng);

Parameters

type	Here, nn ranges from 01 to 0F. 01 to 08 are the known types of text event, while 09 to 0F are
	unrecognized text events. Other values are treat as in m2m_mmisc().
leng	Provides the number of bytes in the event.
mess	Provides a pointer to the event bytes.

Returns

Returns true, always.

Definition at line 714 of file midicvt_m2m.c.

9.17.2.13 int m2m_noff (int chan, int pitch, int vol)

Callback function implementing Mf_off().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0x8n .

Very similar to Note-On messages [see m2m_non()].

In our sample file, ex1.mid, there are no Note-Off messages, only Note-On messages with a velocity of 0.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns true, always.

Definition at line 371 of file midicvt m2m.c.

9.17.2.14 int m2m_non (int chan, int pitch, int vol)

Callback function implementing Mf_on().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0x9n .

The MIDI bytes for a note on message are 4 in number:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Note on byte. 0x9n . This byte is a status byte having two parts:
 - The first (most significant) nybble of this byte is 0x9.
 - The least significant nybble holds the channel number, ranging from 0x0 to 0xF. However, in our sample file, ex1.mid, there see to be notes in which the note-on byte is *missing*!!! This may be correlated to having a note velocity of 0, but not sure about that. There are no Note-Off messages in that file, by the way.
- 3. Note value byte. This value ranges from 0 to 127.
- 4. Note velocity byte. This value ranges from 0 to 127. It seems that a note off can be made by setting this value to zero. Again, not sure about that.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns true, always.

Definition at line 335 of file midicvt m2m.c.

9.17.2.15 int m2m_parameter (int chan, int control, int value)

Callback function implementing Mf_parameter().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xBn .

This function prints the Control Change message. This message has different parameters than the Note On/Off messages.

The MIDI bytes for a control-change message are 4 in number:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Control-change byte. 0xBn . This byte is a status byte having two parts, the command nybble and the channel nybble.
- 3. Control-change value byte. This value ranges from 0 to 127. It determines which controller (e.g. pitch or sustain) is changed.
- 4. Controller value byte. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
control	Provides the MIDI controller number to write.

value	Provides the MIDI controller parameter value to write.
Value	rioridod the imbreditioner parameter value to imite.

Returns

Returns true, always.

Definition at line 450 of file midicvt m2m.c.

9.17.2.16 int m2m_pitchbend (int chan, int lsb, int msb)

Callback function implementing Mf pitchbend().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xEn .

- Ec 11 mm. Pitch Wheel Change. Provides the least significant and most significant 14 bits.
- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Pitch-bend byte. 0xEn .
- 3. Pitch, least-significat value byte. This value ranges from 0 to 127. It provides the lowest 7 bits of the pitch-bend parameter.
- 4. Pitch, most-significat value byte. It provides the highest 7 bits of the pitch-bend parameter.

Parameters

chan	Provides the channel number to write.
Isb	Provides the least-significant bits of the MIDI pitch-wheel value to write.
msb	Provides the most-significant bits of the MIDI pitch-wheel value to write.

Returns

Returns true, always.

Definition at line 493 of file midicvt_m2m.c.

9.17.2.17 int m2m_pressure (int chan, int pitch, int pressure)

Callback function implementing Mf_pressure().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xAn .

Very similar to Note-On messages [see m2m_non()].

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
pressure	Provides the MIDI polyphonic key pressure value to write.

Returns

Returns true, always.

Definition at line 404 of file midicvt_m2m.c.

9.17.2.18 int m2m_program (int chan, int program)

Callback function implementing Mf_program().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xCn pp.

A program-change (patch change) command has the following 3 bytes:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Program-change byte. 0xCn .
- 3. Program/patch number byte nn. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
program	Provides the patch/program number to write.

Returns

Returns true, always.

Definition at line 528 of file midicvt_m2m.c.

9.17.2.19 static int m2m_smpte (int hr, int mn, int se, int fr, int ff) [static]

Callback function implementing Mf smpte().

Prints "SMPTE" and each of the parameters shown below, to standard output.

Parameters

hr	Provides the hour of the SMPTE time at which the track chunk is supposed to start. It should
	be present at the beginning of the track, before any non-zero delta times, and before any
	transmitable MIDI events.
mn	Provides the minutes of the SMPTE time.
se	Provides the seconds of the SMPTE time.
fr	Provides the frames of the SMPTE time.
ff	Provides the fractional frames of the SMPTE time, in 100ths of a frame, even in SMPTE-
	based tracks which specify as different frame subdivision for delta times

Returns

Returns true, always.

Definition at line 960 of file midicvt_m2m.c.

9.17.2.20 static int m2m_sysex (int leng, char * mess) [static]

Callback function implementing Mf_sysex().

This function prints "SysEx" and then a stream of bytes, in hex format, to standard output.

Command: 0xF0 .

The format of this event is roughly as follows:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. System-exclusive byte. 0xF0 .

- 3. Manufacturer's code. A 7-bit value, highest bit is 0.
- 4. Data bytes. A series of 7-bit values.
- 5. EOS (End-of-System-exclusive) byte. 0xF7 .

Parameters

leng	Provides the number of bytes in the message.
mess	Provides a pointer to the message bytes.

Returns

Returns true, always.

Definition at line 596 of file midicvt_m2m.c.

```
9.17.2.21 static int m2m_tempo ( long tempo ) [static]
```

Callback function implementing Mf_tempo().

Prints the string "Tempo" followed by the tempo value, to standard output.

Command: FF 51 03 tt tt tt.

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Meta-event byte. 0xFF .
- 3. End-of-track marker. 0x51 .
- 4. Length byte. 0x03 .
- 5. Data bytes. There are three data bytes that specify the tempo in "microseconds per MIDI quarter-note" or "24ths of a microsecond per MIDI clock". Chew on this conversion: 07 a1 20 == 500000 usec/quarter note == 1/2 second per quarter note == 120 bpm (beats per minute), where each quarter note is a beat.

Note that we don't need to use mf w meta event() here, as a more specific function, mf w tempo() can be used.

Parameters

tempo	Provides the tempo value as a single integer.
-------	---

Returns

Returns true, always.

Definition at line 874 of file midicvt_m2m.c.

```
9.17.2.22 static int m2m_timesig ( int nn, int dd, int cc, int bb ) [static]
```

 $Callback\ function\ implementing\ Mf_timesig().$

Prints the string "TimeSig" followed by the four value needed for a key signature, to standard output.

Command: FF 58 04 nn dd cc bb.

As an example, this sequence of bytes:

FF 58 04 06 03 24 08

This is the complete event for 6/8 time, where the metronome clicks every three eighth-notes, but there are 24 clocks per quarter-note, 72 to the bar. That is, 6/8 time (8 is 2 to the 3rd power, so this is 06 03), 36 MIDI clocks per dotted-quarter (24 hex!), and eight notated 32nd-notes per quarter-note.

Parameters

nn	Provides the numerator of the time signature as it would be notated.
dd	Provides the denominator of the time signature as it would be notated. The denominator is a
	negative power of two, where 2 represents a quarter note, 3 represents an eighth note
СС	Provides the number of MIDI clock in a metronome click.
bb	The number of notated 32nd notes in a MIDI quarter-note (a MIDI quarter note is 24 MIDI
	clocks).

Returns

Returns true, always.

Definition at line 918 of file midicvt_m2m.c.

9.17.2.23 static int m2m_trend (long header_offset, unsigned long track_size) [static]

Callback function implementing Mf_endtrack().

This function write "TrkEnd" and a newline to standard output, and decrements the global "tracks to do" counter. Note that there is also a m2m_meot() function that we do not use. That function outputs the end-of-track found in the input MIDI file, but we need to manufacturer our own end-of-track..

In MIDI, the end-of-track marker is three bytes, ff 2f 00.

Oddity:

Some MIDI files end with a 0a byte as well.

Parameters

header_offset	Provides the offset in the output file where the "MTrk" and track length were tentatively written.
track_size	Provides the track-size that libmidifile actually generated. However, note that this size should
	also include the end-of-track meta-event written in this function, and doesn't, so we have to
	add the length of that event. We don't really need this parameter, since we have access
	(currently) to the global counter s Mf numbyteswritten.

Returns

Returns true, unless the file-seeks into the stdout-redirect file fail.

Definition at line 256 of file midicvt m2m.c.

9.17.2.24 static int m2m_trstart (void) [static]

Callback function implementing Mf starttrack().

This function writes "MTrk" and a newline to standard output and increments the global track number counter.

This marker is a 4-byte unterminated ASCII marker.

Returns

Returns true, always.

Definition at line 203 of file midicvt_m2m.c.

9.17.2.25 void midicvt_initfuncs_m2m (void)

Makes the function assignments needed by the midifile library when converting a MIDI file to text.

We already handle the end of track. See m2m_trend for an explanation.

 $Mf_eot = m2m_meot;$


Definition at line 1011 of file midicvt_m2m.c.

9.18 midicvt_m2m.h File Reference


This module provides functions for a basic MIDI-to-MIDI conversion application.

```
#include <stdio.h>
#include <midicvt_macros.h>
#include <midifilex.h>
```

Include dependency graph for midicvt_m2m.h:



This graph shows which files directly or indirectly include this file:



Functions

· void midicvt_initfuncs_m2m (void)

Makes the function assignments needed by the midifile library when converting a MIDI file to text.

• int m2m_non (int chan, int pitch, int vol)

 ${\it Callback \ function \ implementing \ Mf_on()}.$

• int m2m_noff (int chan, int pitch, int vol)

Callback function implementing Mf_off().

• int m2m_pressure (int chan, int pitch, int pressure)

Callback function implementing Mf_pressure().

int m2m_program (int chan, int program)

Callback function implementing Mf_program().

• int m2m_parameter (int chan, int control, int value)

Callback function implementing Mf_parameter().

• int m2m_pitchbend (int chan, int lsb, int msb)

Callback function implementing Mf_pitchbend().

• int m2m_chanpressure (int chan, int pressure)

Callback function implementing Mf_chanpressure().

9.18.1 Detailed Description

This module provides functions for a basic MIDI-to-MIDI conversion application.

Library midicvt application portion of libmidifilex

Author(s) Chris Ahlstrom and many others; see documentation

Date 2014-04-29

Last Edits 2014-05-13

Version

\$Revision\$ License GNU GPL

9.18.2 Function Documentation

9.18.2.1 int m2m_chanpressure (int chan, int pressure)

Callback function implementing Mf chanpressure().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xDn .

A channel-pressure command has the following 3 bytes:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Channel-pressure byte. 0xDn .
- 3. Channel-pressure value byte. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
pressure	Provides the patch/program number to write.

Returns

Returns true, always.

Definition at line 561 of file midicvt_m2m.c.

9.18.2.2 int m2m_noff (int chan, int pitch, int vol)

Callback function implementing Mf_off().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0x8n .

Very similar to Note-On messages [see m2m_non()].

In our sample file, ex1.mid, there are no Note-Off messages, only Note-On messages with a velocity of 0.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns true, always.

Definition at line 371 of file midicvt m2m.c.

9.18.2.3 int m2m_non (int chan, int pitch, int vol)

Callback function implementing Mf on().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0x9n .

The MIDI bytes for a note on message are 4 in number:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Note on byte. 0x9n . This byte is a status byte having two parts:
 - The first (most significant) nybble of this byte is 0x9.
 - The least significant nybble holds the channel number, ranging from 0x0 to 0xF. However, in our sample file, ex1.mid, there see to be notes in which the note-on byte is *missing*!!! This may be correlated to having a note velocity of 0, but not sure about that. There are no Note-Off messages in that file, by the way.
- 3. Note value byte. This value ranges from 0 to 127.
- 4. Note velocity byte. This value ranges from 0 to 127. It seems that a note off can be made by setting this value to zero. Again, not sure about that.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns true, always.

Definition at line 335 of file midicvt_m2m.c.

9.18.2.4 int m2m_parameter (int chan, int control, int value)

Callback function implementing Mf_parameter().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xBn .

This function prints the Control Change message. This message has different parameters than the Note On/Off messages.

The MIDI bytes for a control-change message are 4 in number:

1. Delta-time byte. A typical value is 0x60 (96).

2. Control-change byte. 0xBn . This byte is a status byte having two parts, the command nybble and the channel nybble.

- 3. Control-change value byte. This value ranges from 0 to 127. It determines which controller (e.g. pitch or sustain) is changed.
- 4. Controller value byte. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
control	Provides the MIDI controller number to write.
value	Provides the MIDI controller parameter value to write.

Returns

Returns true, always.

Definition at line 450 of file midicvt_m2m.c.

9.18.2.5 int m2m_pitchbend (int chan, int lsb, int msb)

Callback function implementing Mf_pitchbend().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xEn .

- Ec 11 mm. Pitch Wheel Change. Provides the least significant and most significant 14 bits.
- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Pitch-bend byte. 0xEn .
- 3. Pitch, least-significat value byte. This value ranges from 0 to 127. It provides the lowest 7 bits of the pitch-bend parameter.
- 4. Pitch, most-significat value byte. It provides the highest 7 bits of the pitch-bend parameter.

Parameters

chan	Provides the channel number to write.
Isb	Provides the least-significant bits of the MIDI pitch-wheel value to write.
msb	Provides the most-significant bits of the MIDI pitch-wheel value to write.

Returns

Returns true, always.

Definition at line 493 of file midicvt_m2m.c.

9.18.2.6 int m2m_pressure (int chan, int pitch, int pressure)

 $Callback\ function\ implementing\ Mf_pressure().$

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xAn .

Very similar to Note-On messages [see m2m_non()].

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
pressure	Provides the MIDI polyphonic key pressure value to write.

Returns

Returns true, always.

Definition at line 404 of file midicvt m2m.c.

9.18.2.7 int m2m_program (int chan, int program)

Callback function implementing Mf_program().

No longer static, so that it can be using in the C++ program midicvtpp.

Command: 0xCn pp.

A program-change (patch change) command has the following 3 bytes:

- 1. Delta-time byte. A typical value is 0x60 (96).
- 2. Program-change byte. 0xCn .
- 3. Program/patch number byte nn. This value ranges from 0 to 127.

Parameters

chan	Provides the channel number to write.
program	Provides the patch/program number to write.

Returns

Returns true, always.

Definition at line 528 of file midicvt_m2m.c.

9.18.2.8 void midicvt_initfuncs_m2m (void)

Makes the function assignments needed by the midifile library when converting a MIDI file to text.

We already handle the end of track. See m2m_trend for an explanation.


 $Mf_eot = m2m_meot;$

Definition at line 1011 of file midicvt_m2m.c.

9.19 midicvt_macros.h File Reference

This module provides macros for generating simple messages, MIDI parameters, and more.

This graph shows which files directly or indirectly include this file:



Macros

• #define MIDI_NOTE_MIN 0

MIDI Manifest Constants:

#define MIDI_NOTE_COUNT (MIDI_NOTE_MAX + 1)

Defines the maximum number of unique MIDI notes.

• #define MIDI_EVENT_NOTE_OFF 0

Defines the values of the MIDI events "note off" and "note on".

#define MIDI_NOTE_OCTAVE 12

Defines the number of notes in a MIDI octave.

• #define MIDI NOTE(x) ((char) (x))

Converts an integer expression to a MIDI note.

• #define MIDI VELOCITY MIN 0

Defines some standard velocity values.

• #define MIDI UNINITIALIZED (-1)

Defines a value used to indicate that certain values are still in their uninitialized state.

• #define MIDI NOTE ILLEGAL (-1)

Defines a value used to indicate that a note function returned an illegal note.

• #define nullptr 0

Language macros:

#define not_nullptr(x) ((x) != nullptr)

Provides a way to declare functions as having either a C++ or C interface.

• #define is_nullptr(x) ((x) == nullptr)

Test for being an invalid pointer.

• #define false 0

Provides the "false" value of the wbool_t type definition.

• #define true 1

Provides the "true" value of the wbool_t type definition.

#define errprint(x) fprintf(stderr, "? %s\n", x)

Provides an error reporting macro (which happens to match Chris's XPC error function.

• #define errprintf(fmt, x) fprintf(stderr, fmt, x)

Provides an error reporting macro that requires a sprintf() format specifier as well.

#define warnprint(x) fprintf(stderr, "! %s\n", x)

Provides a warning reporting macro (which happens to match Chris's XPC error function.

#define warnprintf(fmt, x) fprintf(stderr, fmt, x)

Provides an error reporting macro that requires a sprintf() format specifier as well.

• #define infoprint(x) fprintf(stderr, "* %s\n", x)

Provides an information reporting macro (which happens to match Chris's XPC information function.

• #define infoprintf(fmt, x) fprintf(stderr, fmt, x)

Provides an error reporting macro that requires a sprintf() format specifier as well.

Typedefs

· typedef int cbool_t

A more obvious boolean type.

9.19.1 Detailed Description

This module provides macros for generating simple messages, MIDI parameters, and more.

Library libmidifilex

Author(s) Chris Ahlstrom and other authors; see documentation

Date 2013-11-17

Last Edits 2014-04-20

Version

\$Revision\$ License GNU GPL

The macros in this file cover:

- · Default values of waonc parameters.
- · MIDI manifest constants.
- · Language-support macros.
- · Error and information output macros.

Copyright (C) 2013-2013 Chris Ahlstrom ahlstrom@users.sourceforge.net

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 675 Mass Ave, Cambridge, MA 02139, USA.

9.19.2 Macro Definition Documentation

9.19.2.1 #define MIDI_NOTE_MIN 0

MIDI Manifest Constants:

The first set of macros provides default values for the minimum/maximum detection code. We want to be able to know the highest and lowest MIDI notes that were generated, as a help to running the application again.

Definition at line 50 of file midicvt_macros.h.

9.19.2.2 #define not_nullptr(x) ((x) != nullptr)

Provides a way to declare functions as having either a C++ or C interface.

Test for being a valid pointer.

Definition at line 136 of file midicvt macros.h.

9.19.2.3 #define nullptr 0

Language macros:

Provides an alternative to NULL.

Definition at line 110 of file midicvt_macros.h.

9.20 midicvt_main.c File Reference

This module creates the midicvt program for translating between MIDI files and text files.

```
#include <midicvt_base.h>
#include <midicvt_helpers.h>
#include <midicvt_globals.h>
#include <midicvt_m2m.h>
Include dependency graph for midicvt_main.c:
```

midicvt_main.c

midicvt_main.c

midicvt_m2m.h

midicvt_globals.h

midicvt_macros.h

stdio.h

setjmp.h

Functions

• int main (int argc, char *argv[])

Provides the entry-point for the midicvt program.

Variables

static const char *const s_help_version = "midicvt v 0.3 2015-08-14"
 Version string.

9.20.1 Detailed Description

This module creates the midicvt program for translating between MIDI files and text files.

Library midicvt application

Author(s) Major modifications by Chris Ahlstrom

Date 2014-04-09

Last Edits 2015-08-14

Version

\$Revision\$ License GNU GPL

By translating a MIDI file to a text file, midicvt allows one to use standard UNIX/Linux/OSX/Windows tools to modify a MIDI file. For example, one can write a script to re-map the track that contains a non-standard MIDI drum kit into a General MIDI drumkit. This can free the user from having to buy a proprietary application that includes that ability as one of its "features".

This program was derived from the midicomp project, which itself has a heritage of legacy code, some dating back to the Atari ST! Another project derived from midicomp is the midi2text project. That project takes some iffy shortcuts, so the only features taken from that project are bug-fixes, and [SOON] the ability to call the program using different app-names.

This program also takes advantage of GNU autotools, and refactors the global variables into their own module, and the midifile project into its own library.

Finally, Doxygen markup is being added to make it a bit easier to grok this project. It's all just cleanup, but I had fun doing it.

9.20.2 Function Documentation

```
9.20.2.1 int main ( int argc, char * argv[] )
```

Provides the entry-point for the midicvt program.

Parameters

argc	Provides the standard count of the number of command-line arguments, including the name of the program.
argv	Provides the command-line arguments as an array of pointers.

Returns

Returns a 0 value if the application succeeds, and a non-zero value otherwise.


Definition at line 85 of file midicvt main.c.

9.21 midicvtpp_main.cpp File Reference

This module creates the midicvtpp program for translating between MIDI files and text files, and doing some basic remapping operations.

```
#include <csvarray.hpp>
#include <initree.hpp>
#include <iniwriting.hpp>
#include <midicvt_base.h>
#include <midicvt_helpers.h>
#include <midicvt_globals.h>
#include <midicvt_m2m.h>
#include <midimapper.hpp>
```

Include dependency graph for midicvtpp_main.cpp:



Functions

static void midicvtpp_help ()

Provides the help text for the midicvt program.

• static bool midicvtpp_parse (int argc, char *argv[])

Parses midicvtpp the command-line for options.

• int main (int argc, char *argv[])

Provides the entry-point for the midicvtpp program.

Variables

• static const char *const s_help_version = "midicvtpp v 0.3 2015-07-22"

Provides the version string for this program.

static const char *const gs help usage 1

Addition help string, which supplements the help for the C program midicvt, contained in libmidifilex/src/midicvt_ helpers.h.

static bool s_write_csv_drum = false

Holds the flag needed for the -csv-drum options.

• static bool s_write_csv_patch = false

Holds the flag needed for the -csv-patch options.

static std::string s_csv_in_filename

For the -csv-xxxx options, holds the name of the input CSV (comma-separated value) file.

static std::string s_ini_out_filename

For the -csv-xxxx options, holds the name of the output INI file.

• static std::string s_ini_in_filename = ""

For the -m2m option, holds the name of the input INI file that contains the MIDI mapping information for the MIDI-to-MIDI conversion.

static bool s_m2m_reversal = false

Indicates that the -m2m mapping will be treated as a reverse mapping, and is specified by the -reverse option.

static std::string s_mapping_name = "midicvtpp"

Provides the name of the MIDI remapping process.

• static int s_filter_channel = -1

Provides the channel number to be affected by channel extraction (-extract) or rejection (-reject).

static bool s_rejection_on = false

Indicates if the filtered channel is to be rejected (as opposed to extracted.

9.21.1 Detailed Description

This module creates the midicvtpp program for translating between MIDI files and text files, and doing some basic remapping operations.

Library midicvtpp application

Author(s) Chris Ahlstrom

Date 2014-04-19

Last Edits 2015-07-22

Version

\$Revision\$ License GNU GPL

This C++ program extends the C program midicvt by providing some remapping functionality.

This can save the user from having to create an Awk or Perl script to do some common remapping operations.

9.21.2 Function Documentation

9.21.2.1 int main (int argc, char * argv[])

Provides the entry-point for the midicvtpp program.

Parameters

argc	Provides the standard count of the number of command-line arguments, including the name
	of the program.
argv	Provides the command-line arguments as an array of pointers.

Returns

Returns a 0 value if the application succeeds, and a non-zero value otherwise.

Definition at line 333 of file midicvtpp_main.cpp.

```
9.21.2.2 static void midicvtpp_help( ) [static]
```

Provides the help text for the midicvt program.

Parameters

version	Provides the optional version information.
---------	--

Definition at line 96 of file midicvtpp_main.cpp.

```
9.21.2.3 static bool midicvtpp_parse ( int argc, char * argv[] ) [static]
```

Parses midicvtpp the command-line for options.

First, calls midicvt_parse() to get the midicvt options, and then parses for the the midicvtpp-specific options.

Parameters

argc	The standard argument count for the command-line.
argv	The standard argument list for the command-line.

Returns

Returns 0 if the program succeeded, and a non-zero number if the program fails or help was obtained.

Definition at line 188 of file midicvtpp main.cpp.

9.21.3 Variable Documentation

```
9.21.3.1 const char* const s_help_version = "midicvtpp v 0.3 2015-07-22" [static]
```

Provides the version string for this program.

Please leave "midicvtpp" as the first characters of this version string. The midicvt command-line parser checks this value if C++-only options are provided.

Definition at line 60 of file midicvtpp_main.cpp.

```
9.21.3.2 std::string s_ini_in_filename = "" [static]
```

For the -m2m option, holds the name of the input INI file that contains the MIDI mapping information for the MIDI-to-MIDI conversion.

The default name used to be "../doc/GM_PSS-790_Drums.ini", useful mainly for testing. But we want to be able to do –m2m without requiring an INI file, in the same way the C code does it.

Definition at line 138 of file midicvtpp_main.cpp.

```
9.21.3.3 std::string s_mapping_name = "midicvtpp" [static]
```

Provides the name of the MIDI remapping process.

This name is just a tag name for output, and defaults to "midicvtpp". However, the –testing option changes it to "testing", which is an internal signal for unknown purposes.

Definition at line 154 of file midicvtpp_main.cpp.

```
9.21.3.4 bool s_write_csv_drum = false [static]
```

Holds the flag needed for the -csv-drum options.

See the help text for this option.

Definition at line 106 of file midicvtpp_main.cpp.

```
9.21.3.5 bool s_write_csv_patch = false [static]
```

Holds the flag needed for the -csv-patch options.

See the help text for this option.


Definition at line 113 of file midicvtpp_main.cpp.

9.22 midifilex.c File Reference

This module provides functions for handling the reading and writing of MIDI files.

```
#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#include "midicvt_globals.h"
#include "midicvt_helpers.h"
#include "midifilex.h"
```

Include dependency graph for midifilex.c:



Functions

• static void mferror (char *s)

Reports an error if the Mf_error callback has been assigned, then exits with an error-code of 1.

static void mfreport (char *s)

Reports an information message.

- static cbool_t mfreportable (void)
- static void badbyte (int c)

Provides an error report for a bad byte.

• static int eputc (unsigned char c)

Writes a single character.

static void biggermsg (void)

Re-allocates the message buffer by the standard increment of 128 bytes.

static void msginit (void)

Sets s_message_index to 0.

static char * msg (void)

Provides a pointer to the message buffer.

static int msgleng (void)

Provides the current index into the message buffer.

static void msgadd (int c)

Adds a character to the message buffer.

• static void chanmessage (int status, int c1, int c2)

Handles a channel message.

static void sysex (void)

Handle a system-exclusive message.

static long readvarinum (void)

Read a varying-length number.

• static long to32bit (int c1, int c2, int c3, int c4)

Convert a quad of integers into a 32-bit number.

static short int to16bit (int c1, int c2)

Convert a duo of integers into a 16-bit number.

• static long int read32bit (void)

Reads four bytes and converts them to a 32-bit number.

static short int read16bit (void)

Reads two bytes and converts them to a 16-bit number.

void write32bit (unsigned long data)

write32bit() and write16bit() are used to make sure that the byte order of the various data types remains constant between machines.

static void write16bit (int data)

Writes two bytes of data, one byte at a time.

static void writevarinum (unsigned long value)

Write multi-length bytes to MIDI format files.

· static void metaevent (int type)

Handles a meta-event.

static int readmt (char *s)

Reads through the "MThd" or "MTrk" header string.

• static int readheader (void)

Reads a header chunk.

static cbool_t readtrack (void)

Reads a track chunk.

· void mfread (void)

Calls readheader(), then calls readtrack() while there is data to be read.

• void midifile (void)

Provided for backward compatibility with the original library.

void mf_w_track_chunk (int which_track, FILE *fp, int(*wtrack)(void))

Writes a track chunk.

void mf_w_track_start (int which_track, FILE *fp)

Reads and writes track information.

void mf_w_header_chunk (int format, int ntracks, int division)

Writes a header chunk.

• void mfwrite (int format, int ntracks, int division, FILE *fp)

mfwrite() is the only function you'll need to call to write out a MIDI file.

• int mf_w_midi_event (unsigned long delta_time, unsigned int type, unsigned int chan, unsigned char *data, unsigned long size)

Library routine to mf_write a single MIDI track event in the standard MIDI file format.

• int mf_w_meta_event (unsigned long delta_time, unsigned char type, unsigned char *data, unsigned long size)

Library routine to mf_write a single meta event in the standard MIDI file format.

void mf w tempo (unsigned long delta time, unsigned long tempo)

Writes the tempo data.

• unsigned long mf_sec2ticks (float secs, int division, unsigned int tempo)

Converts seconds to ticks.

• float mf ticks2sec (unsigned long ticks, int division, unsigned int tempo)

Provides the inverse of mf sec2ticks.

static cbool_t readtrack_m2m (void)

Reads a track chunk for MIDI-to-MIDI conversion.

void mftransform (void)

This function provides an alternative to mfread() to better handle direct MIDI-to-MIDI conversions.

Variables

int(* Mf_getc)(void) = nullptr

Functions to be called while processing and writing the MIDI file.

int Mf_nomerge = 0

1 => continue'ed system exclusives are not collapsed.

• long Mf_currtime = 0L

Current time in delta-time units.

• static char * s_message_buffer = nullptr

The code below allows collection of a system exclusive message of arbitrary length.

• static int s_message_size = 0

Holds the size of the currently allocated message buffer.

• static int s_message_index = 0

Holds the index of next available location in s_message_buffer.

static int s_chantype []

Provides a helper array for the readtrack() and readtrack_m2m() functions.

• static int s_laststat = 0

Holds the last status code.

static int s_lastmeta = 0

Holds the last meta event type.

static long s_track_header_offset = 0

Saves the offset of the header portion of the current track.

9.22.1 Detailed Description

This module provides functions for handling the reading and writing of MIDI files.

Library midicvt application

Author(s) Other authors (see below), with modifications by Chris Ahlstrom,

Date 2014-04-08

Last Edits 2015-08-20

Version

\$Revision\$ License GNU GPL

This file is based on midifile.c of the midifile library written by Tim Thompson (tjt@blink.att.com) and updated by Michael Czeiszperger (mike@pan.com). However, there were some bugs in the write code and Piet (see below) added some features he needed. He also changed some of the names to cope with the 7-character limit for external identifiers in the Sozobon compiler. He made an updated version of the library available, and split the read and write portions. However, he ended up with two midifile.c modules, each having differences, including differences that could cause bugs.

Chris (see below) updated the code to more modern C conventions (there's still more to do, such as adding more "const" items) and tried to improved the readability of the code). Also got a start on adding Doxygen markup to generate a more readable reference manual. Also added a Mf_report function pointer, to be enabled for easier diagnosis of MIDI conversion.

```
Piet van Oostrum, Dept of Computer Science, Utrecht University, P.O. Box 80.089, 2508 TB Utrecht, The Netherlands email: piet@cs.ruu.nl

Chris Ahlstrom, Charleston SC, USA email: ahlstromcj@gmail.com
```

Discussion:

For converting a MIDI file to text, the code calls mfread(), which reads the MIDI file and then calls the set of callbacks (in the midicvt_base.c module) that convert the output to human-readable form.

For converting the human-readable text to MIDI, the code calls midicvt_compile(), which reads the header text. Then it calls mfwrite(), which calls essentially only the my_writetrack() callback. That callback knows how to parse the human-readable data and generate MIDI output for it.

When converting directly from MIDI to MIDI, we have two choices:

- Call mfread(), replacing the text-output callbacks in midicvt_base.c with the MIDI-output callbacks in midicvt
 m2m.c. This has some minor issues.
- Call readheader() to get the initial information. Then call mfwrite() with a new write-track routine. However, this routine must also read MIDI [instead of flex data].

So it seems easier to use the first method, and hack it so it works correctly whether the output is human-readable or MIDI.

```
9.22.2 Function Documentation
```

```
9.22.2.1 static void badbyte (int c) [static]
```

Provides an error report for a bad byte.

Since mferror() is called, the application will exit.

Parameters

```
c Provides the bad byte, in integer format.
```

Definition at line 244 of file midifilex.c.

```
9.22.2.2 static void biggermsg ( void ) [static]
```

Re-allocates the message buffer by the standard increment of 128 bytes.

If it cannot allocate the new buffer, then mferror() is called.

Definition at line 331 of file midifilex.c.

9.22.2.3 static void chanmessage (int status, int c1, int c2) [static]

Handles a channel message.

As noted in the description of the *status* parameter, there are various supported messages. Depending on the type of message, one of the following callback calls will be made:

```
(void) (*Mf_off) (chan, c1, c2);
(void) (*Mf_on) (chan, c1, c2);
(void) (*Mf_pressure) (chan, c1, c2);
(void) (*Mf_parameter) (chan, c1, c2);
(void) (*Mf_program) (chan, c1);
(void) (*Mf_chanpressure) (chan, c1);
(void) (*Mf_pitchbend) (chan, c1, c2);
```

Parameters

status	Provides the type+channel byte. The type nybble ranges from 0x80 to 0xe0, and there are
	thus 7 values, corresponding to note-off, note-on, pressure, parameter (control), program
	(patch), channel pressure, and pitch-bend. The channel nybble ranges from 0 to 0xf (i.e.
	MIDI channels 1 to 16).
c1	Provides the first byte of the messsage. Depending on the message type, this value can
	be a MIDI note number, a control number (e.g. the number for a sustain message), a pro-
	gram/patch number, a pitch-wheel change's first value byte), or a system-common message.
c2	Provides the second byte of the messsage. Depending on the message type, this value can
	be a velocity value or control level value, the second bye of a pitch-wheel change, or this
	parameter can be left unused.

Definition at line 459 of file midifilex.c.

```
9.22.2.4 static int eputc (unsigned char c) [static]
```

Writes a single character.

If an error occurs, then this functon calls mferror() and aborts. [But mferror() will call exit().]

Parameters

```
c Provides the character to output with the Mf_putc() callback function.
```

Returns

Returns the return value of Mf_putc(). If this value is EOF, then mferror() is called.

Definition at line 266 of file midifilex.c.

```
9.22.2.5 static void metaevent ( int type ) [static]
```

Handles a meta-event.

The type of event is passed in as a parameter. The message itself is found in msg(), while the length of the message is provided by msgleng().

Parameters

type	Provides the type of meta event. The following value sets are handled:
	0x00. Sequence number. The Mf_seqnum() callback is called.
	 0x01 to 0x0f. Text event. 0x01 to 0x07 are standard text events, while the rest are "unrecognized". The Mf_text() callback is called.
	0x2f. End of track. The Mf_eot() callback is called.
	0x51. Set tempo. The Mf_tempo() callback is called.
	0x54. SMPTE. The Mf_smpte() callback is called.
	0x58. Time signature. The Mf_timesig() callback is called.
	0x59. Key signature. The Mf_keysig() callback is called.
	0x7f. Sequencer specific. The Mf_sqspecific() callback is called.
	Default. Miscellaneous. The Mf_metamisc() callback is called.

Definition at line 772 of file midifilex.c.

9.22.2.6 unsigned long mf_sec2ticks (float secs, int division, unsigned int tempo)

Converts seconds to ticks.

Calculates the value of

```
1000 * secs 1
----- * ----
4 * division tempo
```

Parameters

secs	Provides the seconds value to be converted.
division	Provides the division units.
tempo	Provides the tempo value

Returns

Returns the value of the seconds in ticks, as per the formula shown.

Definition at line 1781 of file midifilex.c.

9.22.2.7 float mf_ticks2sec (unsigned long ticks, int division, unsigned int tempo)

Provides the inverse of mf_sec2ticks.

This routine converts delta times in ticks into seconds. The else statement is needed because the formula is different for tracks based on notes and tracks based on SMPTE times.

Parameters

ticks	Provides the ticks value to be converted.
division	Provides the division units.
tempo	Provides the tempo value

Returns

Returns the value of the ticks in seconds. as per the formula shown.

Warning

If 0, then this should throw an exception!!!

Definition at line 1807 of file midifilex.c.

9.22.2.8 void mf_w_header_chunk (int format, int ntracks, int division)

Writes a header chunk.

This involves writing the following values:

```
-# Header identifier "MThd" (using a tricky long integer), 32
  bits.
-# Chunk length, set to 6. 32 bits.
-# Format. 16 bits.
-# Number of tracks. 16 bits.
-# Divisions. 16 bits.
```

Parameters

format	Provides the format byte to describe the SMF type of the file.
ntracks	Provides the number of tracks in the file.
division	Provides the division parameter of the file.

Definition at line 1446 of file midifilex.c.

9.22.2.9 int mf_w_meta_event (unsigned long delta_time, unsigned char type, unsigned char * data, unsigned long size)

Library routine to mf_write a single meta event in the standard MIDI file format.

The format of a meta event is:

```
<delta-time><FF><type><length><bytes>
```

Parameters

delta_time	Provides the time in ticks since the last event.
type	Provides the type of meta event.
data	Provides A pointer to a block of chars containing the META EVENT, data.
size	Provides the length of the meta-event data.

Returns

Returns the number of bytes written for this meta-event. This functio used to return the *size* parameter, but no one ever used the return value, and we need it in midicvt_m2m.c to adjust the track-size correctly.

Definition at line 1663 of file midifilex.c.

9.22.2.10 int mf_w_midi_event (unsigned long *delta_time*, unsigned int *type*, unsigned int *chan*, unsigned char * *data*, unsigned long *size*)

Library routine to mf_write a single MIDI track event in the standard MIDI file format.

The format is:

Note

This routine uses an array to pass in variable numbers of parameters. Here's an alternate function signature to consider for the future, where the bytes are passed in a variable-parameter list:

```
int mf_w_midi_event
(
   unsigned long delta_time,
   unsigned int type,
   unsigned int chan,
   unsigned long size,
   ...
)
```

Parameters

delta_time	Provides the time in ticks since the last event.
type	Provides the type of event.
chan	Provides The midi channel.
data	Provides A pointer to a block of chars containing the META EVENT, data.
size	Provides The length of the midi-event data.

Returns

Returns the size parameter.

Definition at line 1595 of file midifilex.c.

9.22.2.11 void mf_w_tempo (unsigned long delta_time, unsigned long tempo)

Writes the tempo data.

All tempos are written as 120 beats/minute, expressed in microseconds/quarter note.

Parameters

delta_time	Provides the time in ticks since the last event.
tempo	Provides the temp value to write.

Definition at line 1744 of file midifilex.c.

9.22.2.12 void mf_w_track_chunk (int which_track, FILE * fp, int(*)(void) wtrack)

Writes a track chunk.

This involves the following steps:

```
-# Write "MTrk" (as a tricky #define in midifilex.h)
-# Write 0 as the track length.
-# Call the wtrack callback.
-# Write 0, meta-event, end-of-track, and 0.
-# Go back and rewrite the 32-bit track header.
-# Rewrite the 32-bit track length.
```

Note

Why not use the global Mf_wtrack() function instead of passing it as a parameter here?

Parameters

which_track	Indicates the track number of the track to be written. If -1, then the track is a tempo-track.
fp	The output file descriptor.
wtrack	The function to call to do that actual writing. Usually, this function is either Mf_wtempotrack
	or Mf_wtrack.

Definition at line 1310 of file midifilex.c.

9.22.2.13 void mf_w_track_start (int which_track, FILE * fp)

Reads and writes track information.

Parameters

which_track	Indicates the track number of the track to be written. If -1, then the track is a tempo-track.
fp	The output file descriptor.
wtrack	The function to call to do that actual writing. Usually, this function is either Mf_wtempotrack
	or Mf_wtrack.

Definition at line 1402 of file midifilex.c.

9.22.2.14 static void mferror (char * s) [static]

Reports an error if the Mf_error callback has been assigned, then exits with an error-code of 1.

Parameters

	Dravidae the error massage
S	Provides the error message.
	•

Definition at line 192 of file midifilex.c.

9.22.2.15 void mfread (void)

Calls readheader(), then calls readtrack() while there is data to be read.

Note

This function and mfwrite() are the only non-static functions in this file? Not any more!

Definition at line 1247 of file midifilex.c.

9.22.2.16 static void mfreport (char * s) [static]

Reports an information message.

Useful in debugging. To enable it, simply set Mf_report equal to your reporting function. In its usage inside this module, it acts very similar to the user's callback functions. This makes it easy to compare the user's output to what was actually encountered in the MIDI file.

Parameters

s	Provides the error message.

Definition at line 217 of file midifilex.c.

9.22.2.17 static cbool_t mfreportable(void) [static]

Returns

Returns true if the Mf report function is enabled.

Definition at line 229 of file midifilex.c.

9.22.2.18 void mftransform (void)

This function provides an alternative to mfread() to better handle direct MIDI-to-MIDI conversions.

The mfread() function, with suitable callbacks (see the midicvt_m2m.c module) almost works for MIDI-to-MID← I conversions. However, the existing "write-track" callbacks are a bit difficult to use because they actually require some ability to read input, and don't help keep track of file pointers.

Calls readheader(), which works fine with the m2m_header() callback. then calls readtrack_m2m() while there is data to be read.

Definition at line 1994 of file midifilex.c.

9.22.2.19 void mfwrite (int format, int ntracks, int division, FILE * fp)

mfwrite() is the only function you'll need to call to write out a MIDI file.

First, the Mf_putc() and Mf_wtrack() callbacks are checked to make sure that they have been assigned to callback functions.

Then mf_w_header_chunk(format, ntracks, division) is called.

If the format is SMF 1, then a track chunk is written by passing the Mf_wtempotrack() callback to the mf_w_track ← _chunk() function.

Finally, the rest of the tracks are written by passing the Mf_wtrack() callback to the mf_w_track_chunk() function.

Parameters

format	Indicates the level of SMF (standard MIDI file) support.
	0: Single multi-channel track.
	1: Multiple simultaneous tracks.
	2: One or more sequentially independent single track patterns.
ntracks	Provides the number of tracks in the file.
division	This parameter is kind of tricky, it can represent two things, depending on whether it is positive or negative (bit 15 set or not). If bit 15 of division is zero, bits 14 through 0 represent the number of delta-time "ticks" which make up a quarter note. If bit 15 of division is a one, delta-times in a file correspond to subdivisions of a second similiar to SMPTE and MI DI time code. In this format bits 14 through 8 contain one of four values - 24, -25, -29, or -30, corresponding to the four standard SMPTE and MIDI time code frame per second formats, where -29 represents 30 drop frame. The second byte consisting of bits 7 through 0 corresponds the the resolution within a frame. Refer the Standard MIDI Files 1.0 spec for more details.
fp	This should be the open file pointer to the file you want to write. It will have be a global in order to work with Mf_putc.

Definition at line 1507 of file midifilex.c.

9.22.2.20 void midifile (void)

Provided for backward compatibility with the original library.

This function simply calls mfread().

Definition at line 1265 of file midifilex.c.

9.22.2.21 static char* msg (void) [static]

Provides a pointer to the message buffer.

Returns

Returns the s_message_buffer static variable.

Definition at line 373 of file midifilex.c.

```
9.22.2.22 static void msgadd (int c) [static]
```

Adds a character to the message buffer.

If necessary, it re-allocates a larger message buffer by calling biggermsg().

Parameters

c The character to add to the message buffer.

Definition at line 402 of file midifilex.c.

```
9.22.2.23 static int msgleng ( void ) [static]
```

Provides the current index into the message buffer.

Returns

Returns the value of s_message_index.

Definition at line 386 of file midifilex.c.

```
9.22.2.24 static short int read16bit ( void ) [static]
```

Reads two bytes and converts them to a 16-bit number.

Returns

Returns the total value represented by the two characters.

Definition at line 671 of file midifilex.c.

```
9.22.2.25 static long int read32bit ( void ) [static]
```

Reads four bytes and converts them to a 32-bit number.

• We need to use an actual 32-bit return type for 64-bit systems.

• Do we need to make the temp variables volatile; can the compiler reorder them?

Returns

Returns the total value represented by the four characters.

Definition at line 654 of file midifilex.c.

```
9.22.2.26 static int readheader ( void ) [static]
```

Reads a header chunk.

First, readmt() is called to verify that "MThd" was retrieved from the file. If this succeeds, then the following items are read:

- 1. Length of the header (32 bits). This value is saved in the global variable s_Mf_toberead.
- 2. Format of the header (16 bits).
- 3. Number of tracks (16 bits).
- 4. The division value (16 bits).

The last three values are passed to the Mf_header() callback function as parameters. This function should reduce the value of s_Mf_toberead as bytes are processed.

If s_Mf_toberead is still greater than 0, then the extra characters are flushed by calling egetc() s_Mf_toberead times.

Definition at line 1027 of file midifilex.c.

```
9.22.2.27 static int readmt ( char *s ) [static]
```

Reads through the "MThd" or "MTrk" header string.

Characters are read via the Mf_getc() callback function. If the characters read do not match the expected string, then a fatal error occurs.

Parameters

s Provides the string that is expected to be read from the file.

Returns

Returns the last character obtained, or READMT_EOF if not characters could be read (and the –strict option is in force). Also returns READMT_EOF if the match was unable to be detected. Returns READMT_IGNO \leftarrow RE_NON_MTRK if there is no match, but the –ignore option is active.

Definition at line 959 of file midifilex.c.

```
9.22.2.28 static cbool_t readtrack( void ) [static]
```

Reads a track chunk.

First, readmt() is called to verify that "MTrk" was retrieved from the file. If this succeeds, then this function reads the length of the header (32 bits). This value is saved in the global variable s_Mf_toberead. Then Mf_currtime is set to 0. The Mf_starttrack() callback is called.

While s_Mf_toberead is non-zero, a byte is read and the following events are checked:

- · 0xff. Meta event.
- 0xf0. System exclusive message.
- 0xf7. Sysex continuation or arbitrary data.

A lot of other processing is done (see the code), and then the Mf endtrack() calllback is called.

Note

Be sure to compare this function to the new variant, readtrack m2m().

Returns

Returns true if the "MTrk" marker was found.

Note

The test file ex1.mid has the Note On byte missing from the notes after the first two! However, the note value, which is in c, lets us reach here, and the code then copies status (which currently holds the Note On byte) into c, effectively restoring the Note On byte.

Definition at line 1108 of file midifilex.c.

```
9.22.2.29 static cbool_t readtrack_m2m ( void ) [static]
```

Reads a track chunk for MIDI-to-MIDI conversion.

This function is a modified version of readtrack() that works better for direct MIDI-to-MIDI conversion using the callbacks defined in the midicvt_m2m.c module.

A new function was made from readtrack() in order to better avoid breaking that function for existing functionality.

Returns

Returns true if the "MTrk" marker was found.

Note

The test file ex1.mid has the Note On byte missing from the notes after the first two! However, the note value, which is in c, lets us reach here, and the code then copies status (which currently holds the Note On byte) into c, effectively restoring the Note On byte.

Definition at line 1847 of file midifilex.c.

```
9.22.2.30 static long readvarinum ( void ) [static]
```

Read a varying-length number.

A variable-length quantity is a MIDI number that is represented by a string of bytes where all bytes but the last have bit 7 set. In each byte, only the 7 least-significant bits provide the numeric value.

- Numbers between 0 and 127 (0x7F) are represented by a single byte.
- 0x80 is represented as "0x81 0x00".
- 0x0FFFFFF (the largest number) is represented as "0xFF 0xFF 0xFF 0x7F".

This function doesn't return the number of characters it took, it returns the value of the varying-length number.

Definition at line 572 of file midifilex.c.

```
9.22.2.31 static void sysex (void ) [static]
```

Handle a system-exclusive message.

The msgleng() and msg() values are passed to the Mf_sysex() callback function.

Definition at line 537 of file midifilex.c.

```
9.22.2.32 static short int to 16bit (int c1, int c2) [static]
```

Convert a duo of integers into a 16-bit number.

Parameters

c1	Provides the most-significant portion of the number. This portion gets shifted leftward by 8
	bits once.
c2	Provides the least-significant portion of the number. This portion gets shifted leftward not at
	all.

Returns

The total value represented by the two parameters is returned.

Definition at line 636 of file midifilex.c.

```
9.22.2.33 static long to 32 bit (int c1, int c2, int c3, int c4 ) [static]
```

Convert a quad of integers into a 32-bit number.

Parameters

c1	Provides the most-significant portion of the number. This portion gets shifted leftward by 8
	bits three times.
c2	Provides the second portion of the number.
c3	Provides the third portion of the number.
c4	Provides the least-significant portion of the number. This portion gets shifted leftward not at
	all.

Returns

The total value represented by the four parameters is returned.

Definition at line 611 of file midifilex.c.

```
9.22.2.34 static void write16bit (int data) [static]
```

Writes two bytes of data, one byte at a time.

Parameters

data Provide	es the 16 bits of data to be written, one byte at a time.
--------------	---

Definition at line 711 of file midifilex.c.

```
9.22.2.35 void write32bit (unsigned long data)
```

write32bit() and write16bit() are used to make sure that the byte order of the various data types remains constant between machines.

This helps make sure that the code will be portable from one system to the next. It is slightly dangerous that it assumes that longs have at least 32 bits and ints have at least 16 bits, but this has been true at least on PCs, UNIX machines, and Macintosh's.

Todo Provide the proper 32-bit data types needed to do this more portably.

Parameters

data	Provides the 32 bits of data to be written, one byte at a time.

Definition at line 695 of file midifilex.c.

```
9.22.2.36 static void writevarinum (unsigned long value) [static]
```

Write multi-length bytes to MIDI format files.

We changed the name of this function from "writevarinum()" to "writevarinum()" to match "readvarinum()" and cut down on some confusion.

Parameters

```
value Provides the value to be written.
```

Definition at line 728 of file midifilex.c.

9.22.3 Variable Documentation

```
9.22.3.1 int s_chantype[] [static]
```

Initial value:

Provides a helper array for the readtrack() and readtrack_m2m() functions.

This static array is indexed by the high half of a status byte. Its value is either the number of bytes needed (1 or 2) for a channel message, or 0 (meaning it's not a channel message).

Definition at line 1074 of file midifilex.c.

```
9.22.3.2 char* s_message_buffer = nullptr [static]
```

The code below allows collection of a system exclusive message of arbitrary length.

The message buffer is expanded as necessary. The only visible data/routines are msginit(), msgadd(), msg(), msgleng().

Definition at line 309 of file midifilex.c.

```
9.22.3.3 long s_track_header_offset = 0 [static]
```

Saves the offset of the header portion of the current track.


This value is use only for m2m (MIDI-to-MIDI) processing.

Definition at line 1383 of file midifilex.c.


9.23 midifilex.h File Reference

This module provides functions for libmidifilex.

```
#include <stdio.h>
#include <midicvt_macros.h>
Include dependency graph for midifilex.h:
```



This graph shows which files directly or indirectly include this file:



Macros

#define note_off 0x80

Provides lower-case (!) macros for MIDI status commands.

#define damper pedal 0x40

Provides lower-case macros for the 7 bit controllers.

• #define data inc 0x60

Provides parameter values.

#define non_reg_lsb 0x62

Provides parameter selection.

• #define meta event 0xff

Provides standard MIDI Files meta event definitions.

#define Seq_Circuits (0x01) /* Sequential Circuits Inc. */

Provides the manufacturer's ID number.

#define MThd 0x4d546864L

Provides miscellaneous definitions and macros.

Functions

float mf ticks2sec (unsigned long, int, unsigned int)

Provides the inverse of mf_sec2ticks.

• unsigned long mf_sec2ticks (float, int, unsigned int)

Converts seconds to ticks.

void write32bit (unsigned long data)

write32bit() and write16bit() are used to make sure that the byte order of the various data types remains constant between machines.

· void mfread (void)

Calls readheader(), then calls readtrack() while there is data to be read.

void mftransform (void)

This function provides an alternative to mfread() to better handle direct MIDI-to-MIDI conversions.

void mfwrite (int, int, int, FILE *)

mfwrite() is the only function you'll need to call to write out a MIDI file.

void midifile (void)

Provided for backward compatibility with the original library.

• void mf_w_header_chunk (int format, int ntracks, int division)

Writes a header chunk.

void mf_w_track_chunk (int which_track, FILE *fp, int(*wtrack)(void))

Writes a track chunk.

void mf_w_track_start (int which_track, FILE *fp)

Reads and writes track information.

• int mf w midi event (unsigned long, unsigned int, unsigned int, unsigned char *, unsigned long)

Library routine to mf_write a single MIDI track event in the standard MIDI file format.

• void mf_w_tempo (unsigned long, unsigned long)

Writes the tempo data.

• int mf w meta event (unsigned long, unsigned char, unsigned char *, unsigned long)

Library routine to mf_write a single meta event in the standard MIDI file format.

Variables

• int Mf_nomerge

1 => continue'ed system exclusives are not collapsed.

· long Mf_currtime

Current time in delta-time units.

int(* Mf_getc)(void)

Functions to be called while processing and writing the MIDI file.

9.23.1 Detailed Description

This module provides functions for libmidifilex.

Library libmidifilex

Author(s) Chris Ahlstrom and many other authors; see documentation

Date 2014-04-08

Last Edits 2014-05-20

Version

\$Revision\$ License GNU GPL

9.23.2 Macro Definition Documentation

9.23.2.1 #define note_off 0x80

Provides lower-case (!) macros for MIDI status commands.

The most significant bit is 1.

Definition at line 118 of file midifilex.h.

9.23.3 Function Documentation

9.23.3.1 unsigned long mf_sec2ticks (float secs, int division, unsigned int tempo)

Converts seconds to ticks.

Calculates the value of

Parameters

secs	Provides the seconds value to be converted.
division	Provides the division units.
tempo	Provides the tempo value

Returns

Returns the value of the seconds in ticks, as per the formula shown.

Definition at line 1781 of file midifilex.c.

9.23.3.2 float mf_ticks2sec (unsigned long ticks, int division, unsigned int tempo)

Provides the inverse of mf sec2ticks.

This routine converts delta times in ticks into seconds. The else statement is needed because the formula is different for tracks based on notes and tracks based on SMPTE times.

Parameters

ticks	Provides the ticks value to be converted.
division	Provides the division units.
tempo	Provides the tempo value

Returns

Returns the value of the ticks in seconds. as per the formula shown.

Warning

If 0, then this should throw an exception!!!

Definition at line 1807 of file midifilex.c.

9.23.3.3 void mf_w_header_chunk (int format, int ntracks, int division)

Writes a header chunk.

This involves writing the following values:

```
-# Header identifier "MThd" (using a tricky long integer), 32
  bits.
-# Chunk length, set to 6. 32 bits.
-# Format. 16 bits.
-# Number of tracks. 16 bits.
-# Divisions. 16 bits.
```

Parameters

	format	Provides the format byte to describe the SMF type of the file.
ſ	ntracks	Provides the number of tracks in the file.
ſ	division	Provides the division parameter of the file.

Definition at line 1446 of file midifilex.c.

9.23.3.4 int mf_w_meta_event (unsigned long delta_time, unsigned char type, unsigned char * data, unsigned long size)

Library routine to mf write a single meta event in the standard MIDI file format.

The format of a meta event is:

```
<delta-time><FF><type><length><bytes>
```

Parameters

delta_time	Provides the time in ticks since the last event.
type	Provides the type of meta event.
data	Provides A pointer to a block of chars containing the META EVENT, data.
size	Provides the length of the meta-event data.

Returns

Returns the number of bytes written for this meta-event. This functio used to return the *size* parameter, but no one ever used the return value, and we need it in midicvt m2m.c to adjust the track-size correctly.

Definition at line 1663 of file midifilex.c.

9.23.3.5 int mf_w_midi_event (unsigned long *delta_time*, unsigned int *type*, unsigned int *chan*, unsigned char * *data*, unsigned long *size*)

Library routine to mf_write a single MIDI track event in the standard MIDI file format.

The format is:

Note

This routine uses an array to pass in variable numbers of parameters. Here's an alternate function signature to consider for the future, where the bytes are passed in a variable-parameter list:

```
int mf_w_midi_event
(
   unsigned long delta_time,
   unsigned int type,
   unsigned int chan,
   unsigned long size,
   ...
)
```

Parameters

delta_time	Provides the time in ticks since the last event.
type	Provides the type of event.
chan	Provides The midi channel.
data	Provides A pointer to a block of chars containing the META EVENT, data.
size	Provides The length of the midi-event data.

Returns

Returns the size parameter.

Definition at line 1595 of file midifilex.c.

9.23.3.6 void mf_w_tempo (unsigned long delta_time, unsigned long tempo)

Writes the tempo data.

All tempos are written as 120 beats/minute, expressed in microseconds/quarter note.

Parameters

delta_time	Provides the time in ticks since the last event.
tempo	Provides the temp value to write.

Definition at line 1744 of file midifilex.c.

9.23.3.7 void mf_w_track_chunk (int which_track, FILE * fp, int(*)(void) wtrack)

Writes a track chunk.

This involves the following steps:

```
-# Write "MTrk" (as a tricky #define in midifilex.h)
-# Write 0 as the track length.
-# Call the wtrack callback.
-# Write 0, meta-event, end-of-track, and 0.
-# Go back and rewrite the 32-bit track header.
-# Rewrite the 32-bit track length.
```

Note

Why not use the global Mf wtrack() function instead of passing it as a parameter here?

Parameters

which_track	Indicates the track number of the track to be written. If -1, then the track is a tempo-track.
fp	The output file descriptor.
wtrack	The function to call to do that actual writing. Usually, this function is either Mf_wtempotrack
	or Mf_wtrack.

Definition at line 1310 of file midifilex.c.

9.23.3.8 void mf_w_track_start (int which_track, FILE * fp)

Reads and writes track information.

Parameters

which_track	Indicates the track number of the track to be written. If -1, then the track is a tempo-track.
fp	The output file descriptor.
wtrack	The function to call to do that actual writing. Usually, this function is either Mf_wtempotrack
	or Mf_wtrack.

Definition at line 1402 of file midifilex.c.

9.23.3.9 void mfread (void)

Calls readheader(), then calls readtrack() while there is data to be read.

Note

This function and mfwrite() are the only non-static functions in this file? Not any more!

Definition at line 1247 of file midifilex.c.

9.23.3.10 void mftransform (void)

This function provides an alternative to mfread() to better handle direct MIDI-to-MIDI conversions.

The mfread() function, with suitable callbacks (see the midicvt_m2m.c module) almost works for MIDI-to-MID

I conversions. However, the existing "write-track" callbacks are a bit difficult to use because they actually require some ability to read input, and don't help keep track of file pointers.

Calls readheader(), which works fine with the m2m_header() callback. then calls readtrack_m2m() while there is data to be read.

Definition at line 1994 of file midifilex.c.

9.23.3.11 void mfwrite (int format, int ntracks, int division, FILE * fp)

mfwrite() is the only function you'll need to call to write out a MIDI file.

First, the Mf_putc() and Mf_wtrack() callbacks are checked to make sure that they have been assigned to callback functions.

Then mf w header chunk(format, ntracks, division) is called.

If the format is SMF 1, then a track chunk is written by passing the Mf_wtempotrack() callback to the mf_w_track← _chunk() function.

Finally, the rest of the tracks are written by passing the Mf_wtrack() callback to the mf_w_track_chunk() function.

Parameters

format	Indicates the level of SMF (standard MIDI file) support.
	0: Single multi-channel track.
	1: Multiple simultaneous tracks.
	2: One or more sequentially independent single track patterns.
ntracks	Provides the number of tracks in the file.
division	This parameter is kind of tricky, it can represent two things, depending on whether it is positive or negative (bit 15 set or not). If bit 15 of division is zero, bits 14 through 0 represent the number of delta-time "ticks" which make up a quarter note. If bit 15 of division is a one, delta-times in a file correspond to subdivisions of a second similiar to SMPTE and MI → DI time code. In this format bits 14 through 8 contain one of four values - 24, -25, -29, or -30, corresponding to the four standard SMPTE and MIDI time code frame per second formats, where -29 represents 30 drop frame. The second byte consisting of bits 7 through 0 corresponds the the resolution within a frame. Refer the Standard MIDI Files 1.0 spec for more details.
fp	This should be the open file pointer to the file you want to write. It will have be a global in order to work with Mf_putc.

Definition at line 1507 of file midifilex.c.

```
9.23.3.12 void midifile (void)
```

Provided for backward compatibility with the original library.

This function simply calls mfread().

Definition at line 1265 of file midifilex.c.

```
9.23.3.13 void write32bit (unsigned long data)
```

write32bit() and write16bit() are used to make sure that the byte order of the various data types remains constant between machines.

This helps make sure that the code will be portable from one system to the next. It is slightly dangerous that it assumes that longs have at least 32 bits and ints have at least 16 bits, but this has been true at least on PCs, UNIX machines, and Macintosh's.

Todo Provide the proper 32-bit data types needed to do this more portably.

Parameters

dat	Provides the 32 bits of data to be written, one byte at a time.


Definition at line 695 of file midifilex.c.

9.24 midimapper.cpp File Reference

This module provides functions for advanced MIDI/text conversions.

```
#include <stdlib.h>
#include <ininames.hpp>
#include <initree.hpp>
#include <midicvt_globals.h>
#include <midicvt_macros.h>
#include <midicvt_m2m.h>
#include <midifilex.h>
#include <midimapper.hpp>
```

Include dependency graph for midimapper.cpp:



Functions

• static int midimap_non (int chan, int pitch, int vol)

This static C function uses the singleton midipp::midimapper object to remap the channel and pitch values, and passes them to the corresponding callback function defined in the midicvt_m2m.c module.

• static int midimap_noff (int chan, int pitch, int vol)

This static C function uses the singleton midipp::midimapper object to remap the channel and pitch values, and passes them to the corresponding callback function defined in the midicvt_m2m.c module.

static int midimap_pressure (int chan, int pitch, int pressure)

This static C function uses the singleton midipp::midimapper object to remap the channel and pitch values, and passes them to the corresponding callback function defined in the midicvt_m2m.c module.

• static int midimap_patch (int chan, int patch)

Remaps the channel and the program (patch) number, and passes them to the corresponding callback function defined in the midicvt_m2m.c module.

static int midimap_parameter (int chan, int control, int value)

For filtering parameter/control messages.

• static int midimap_pitchbend (int chan, int lsb, int msb)

For filtering pitchbend messages.

• static int midimap_chanpressure (int chan, int pressure)

For filtering channel-pressure messages.

void show_maps (const std::string &tag, const midipp::midimapper &container)

Writes out the contents of the pitch-map container out to stderr.

void midimap_init (midipp::midimapper &mm)

Hooks the midipp::midimapper object provided to the global pointer for such objects, to allow the C routines to be able to use the features of the MIDI mapper.

Variables

• static midipp::midimapper * gs_singleton_midimapper = nullptr

Holds the single pointer to the midipp::midimapper object the caller created.

9.24.1 Detailed Description

This module provides functions for advanced MIDI/text conversions.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-24

Last Edits 2014-05-21

Version

\$Revision\$ License GNU GPL

This module uses some of the libmidifilex callbacks of the C modules in libmidifilex/src/midicvt_base.c, but for the purposes of writing out another MIDI file, rather than a text file. The new MIDI file has certain keys or patches remapped between General MIDI (GM) settings and the settings an old MIDI device such as the Yamaha PSS-790.

Conversion from MIDI to text starts with the (new) C function mftransform().

9.24.2 Function Documentation

9.24.2.1 static int midimap_chanpressure (int chan, int pressure) [static]

For filtering channel-pressure messages.

Parameters

chan	Provides the channel number to write.
pressure	Provides the patch/program number to write.

Returns

Returns the result of the m2m_chanpressure() call. If the channel is not active, then 0 (false) is returned.

Definition at line 1145 of file midimapper.cpp.

9.24.2.2 void midimap_init (midipp::midimapper & mm)

Hooks the midipp::midimapper object provided to the global pointer for such objects, to allow the C routines to be able to use the features of the MIDI mapper.

This function calls midicvt_initfuncs_m2m() to set up the MIDI-to-MIDI callbacks, but then overrides some of them with the C call backs in the rest of this module.

Parameters

mm	Provides the MIDI mapper object to be used.

Definition at line 859 of file midimapper.cpp.

9.24.2.3 static int midimap_noff (int chan, int pitch, int vol) [static]

This static C function uses the singleton midipp::midimapper object to remap the channel and pitch values, and passes them to the corresponding callback function defined in the midicvt m2m.c module.

If the midipp::midimapper object is not hooked in, then the values are passed unchanged.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns the return-value of the corresponding midicvt_m2m callback function.

Definition at line 946 of file midimapper.cpp.

```
9.24.2.4 static int midimap_non (int chan, int pitch, int vol) [static]
```

This static C function uses the singleton midipp::midimapper object to remap the channel and pitch values, and passes them to the corresponding callback function defined in the midicvt m2m.c module.

If the midipp::midimapper object is not hooked in, then the values are passed unchanged. This then yields the same functionality as running the following C program from this library:

```
$ ./midicvt --m2m in.mid out.mid
```

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
vol	Provides the MIDI note velocity to write.

Returns

Returns the return-value of the corresponding midicvt_m2m callback function.

Definition at line 900 of file midimapper.cpp.

9.24.2.5 static int midimap_parameter (int chan, int control, int value) [static]

For filtering parameter/control messages.

Parameters

chan	Provides the channel number to write.
control	Provides the MIDI controller number to write.
value	Provides the MIDI controller parameter value to write.

Returns

Returns the result of the m2m parameter() call. If the channel is not active, then 0 (false) is returned.

Definition at line 1076 of file midimapper.cpp.

```
9.24.2.6 static int midimap_patch ( int chan, int patch ) [static]
```

Remaps the channel and the program (patch) number, and passes them to the corresponding callback function defined in the midicvt_m2m.c module.

If the midipp::midimapper object is not hooked in, then the values are passed unchanged.

Parameters

ſ	chan	Provides the channel number to write.
ſ	patch	Provides the patch/program number to write.

Returns

Returns the return-value of the corresponding midicvt_m2m callback function.

Definition at line 1035 of file midimapper.cpp.

9.24.2.7 static int midimap_pitchbend (int chan, int lsb, int msb) [static]

For filtering pitchbend messages.

Parameters

chan	Provides the channel number to write.
Isb	Provides the least-significant bits of the MIDI pitch-wheel value to write.
msb	Provides the most-significant bits of the MIDI pitch-wheel value to write.

Returns

Returns the result of the m2m_pitchbend() call. If the channel is not active, then 0 (false) is returned.

Definition at line 1113 of file midimapper.cpp.

9.24.2.8 static int midimap_pressure (int chan, int pitch, int pressure) [static]

This static C function uses the singleton midipp::midimapper object to remap the channel and pitch values, and passes them to the corresponding callback function defined in the midicvt_m2m.c module.

If the midipp::midimapper object is not hooked in, then the values are passed unchanged.

Parameters

chan	Provides the channel number to write.
pitch	Provides the MIDI note number to write.
pressure	Provides the MIDI polyphonic key pressure value to write.

Returns

Returns the return-value of the corresponding midicvt_m2m callback function.

Definition at line 992 of file midimapper.cpp.

9.24.2.9 void show_maps (const std::string & tag, const midipp::midimapper & container)

Writes out the contents of the pitch-map container out to stderr.

We can't write to stdout because that is often redirected to a file.

This implementation is a for_each style of looping through the container.

Parameters

	tag	Identifies the object in the human-readable output.
con	tainer	The stringmap through which iteration is done for showing.

Definition at line 693 of file midimapper.cpp.

9.24.3 Variable Documentation

9.24.3.1 midipp::midimapper* gs_singleton_midimapper = nullptr [static]

Holds the single pointer to the midipp::midimapper object the caller created.

Since we're integrating with C code, we can't really use more than one object at a time anyway.


Definition at line 843 of file midimapper.cpp.

9.25 midimapper.hpp File Reference


This module provides functions for advanced MIDI/text conversions.

```
#include <map>
#include <string>
```

Include dependency graph for midimapper.hpp:



This graph shows which files directly or indirectly include this file:



Data Structures

· class midipp::midimapper

This class provides for some basic remappings to be done to MIDI files, using the old and new facilities of libmidifilex.

Functions

- void show_maps (const std::string &tag, const midipp::midimapper &container)

 Writes out the contents of the pitch-map container out to stderr.
- void midimap_init (midipp::midimapper &mm)

Hooks the midipp::midimapper object provided to the global pointer for such objects, to allow the C routines to be able to use the features of the MIDI mapper.

9.25.1 Detailed Description

This module provides functions for advanced MIDI/text conversions.

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-24

Last Edits 2014-05-21

Version

\$Revision\$ License GNU GPL

The mapping process works though static functions that reference a global midimapper object.

This object gets its setup from an INI file. This INI file has an unnamed section with the following format:

```
file-style = sectioned
       setup-name = midicvtpp
       record-count = 51
       map-type = Drum
       gm\_-hannel = 10
       device-channel = 16
The "drum" sections are named for the GM note that is to be
remapped, and the "patch" sections are name for the GM patch/program
number that is to be remapped:
       [ Drum 35 ]
       gm-name = Acoustic Bass Drum
       qm-note = 35
       dev-name = N/A
       dev-note = 35
       gm-equiv = Acoustic Base Drum
       [ Patch 1 ]
       gm-name = Bright Acoustic Piano
       qm-patch = 1
       dev-name = Jazz Organ 1
       dev-patch = 16
       gm-equiv = Drawbar Organ
The gm-equiv fields are currently just a way to see how good the
mapping is. If it matches the gm-name, that mapping is probably
pretty good.
Finally, a facility is provided to move channels around. This is
needed, for example, when converting drums to channel 10, but the
MIDI file already has other music on channel 10. If you don't need
this section, don't define it; it saves processing time.
       [ Channels ]
      ch_01 = 1
       ch_02 = 2
       ch_16 = 16
```

9.25.2 Function Documentation

9.25.2.1 void midimap_init (midipp::midimapper & mm)

Hooks the midipp::midimapper object provided to the global pointer for such objects, to allow the C routines to be able to use the features of the MIDI mapper.

This function calls midicvt_initfuncs_m2m() to set up the MIDI-to-MIDI callbacks, but then overrides some of them with the C call backs in the rest of this module.

Parameters

```
mm | Provides the MIDI mapper object to be used.
```

Definition at line 859 of file midimapper.cpp.

9.25.2.2 void show_maps (const std::string & tag, const midipp::midimapper & container)

Writes out the contents of the pitch-map container out to stderr.

We can't write to stdout because that is often redirected to a file.

This implementation is a for_each style of looping through the container.

Parameters

tag	Identifies the object in the human-readable output.
container	The stringmap through which iteration is done for showing.

Definition at line 693 of file midimapper.cpp.

9.26 midipp_functions.dox File Reference

This document describes the functions and parameters of the libmidipp module.


9.26.1 Detailed Description

This document describes the functions and parameters of the libmidipp module.

9.27 stringmap.cpp File Reference

Library libmidipp

#include <stringmap.hpp>
Include dependency graph for stringmap.cpp:



Functions

• bool midipp::iequal (const std::string &s1, const std::string &s2)

A simple case-insensitive comparison for simple string equality.

• void show (const std::string &tag, const std::string &s)

Writes out the contents of the string to standard output, in a stylized format.

9.27.1 Detailed Description

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-22

Last Edits 2014-05-18

Version

\$Revision\$ License \$XPC_SUITE_GPL_LICENSE\$

This module defines an std::map that uses only std::string as a key value, for easy lookup.

9.27.2 Function Documentation

9.27.2.1 void show (const std::string & tag, const std::string & s)

Writes out the contents of the string to standard output, in a stylized format.

Also see the show_pair() and show() functions in the stringmap.hpp module.

Parameters

tag	A name for the string, to provide context for the human reader.
s	The string to be shown.


Definition at line 83 of file stringmap.cpp.

9.28 stringmap.hpp File Reference


Library libmidipp

#include <algorithm>
#include <map>
#include <string>
#include <stdio.h>

Include dependency graph for stringmap.hpp:



This graph shows which files directly or indirectly include this file:



Data Structures

class midipp::stringmap< VALUETYPE >

Provides an std::map wrapper geared towards using std::string as a key.

Functions

• void show (const std::string &tag, const std::string &s)

Writes out the contents of the string to standard output, in a stylized format.

• bool midipp::iequal (const std::string &s1, const std::string &s2)

A simple case-insensitive comparison for simple string equality.

 $\bullet \ \ \mathsf{template} {<} \mathsf{class} \ \mathsf{VALUETYPE} > \\$

void midipp::show_pair (const typename stringmap < VALUETYPE >::pair &p)

Writes out the contents of an string/VALUETYPE pair.

 $\bullet \ \ \mathsf{template} {<} \mathsf{class} \ \mathsf{VALUETYPE} > \\$

void **midipp::show** (const std::string &tag, const stringmap< VALUETYPE > &container)

Writes out the contents of the property container.

9.28.1 Detailed Description

Library libmidipp

Author(s) Chris Ahlstrom

Date 2014-04-22

Last Edits 2014-05-21

Version

\$Revision\$ License \$MIDIPP_SUITE_GPL_LICENSE\$

This module defines an std::map template class using std::string as a key value.

9.28.2 Function Documentation

9.28.2.1 void show (const std::string & tag, const std::string & s)

Writes out the contents of the string to standard output, in a stylized format.

Also see the show pair() and show() functions in the stringmap.hpp module.

Parameters

tag	A name for the string, to provide context for the human reader.
s	The string to be shown.


Definition at line 83 of file stringmap.cpp.

9.29 t2m_no_flex.c File Reference

This file is to be used instead of the dynamically generated t2mflex.c if there is no flex program installed or if the installed flex is old [e.g 2.5.35 as opposed to 2.5.39 (!)].

```
#include <stdio.h>
#include <string.h>
#include <errno.h>
#include <stdlib.h>
#include <midicvt_base.h>
#include <t2mf.h>
#include <unistd.h>
```

Include dependency graph for t2m_no_flex.c:



Functions

void yyrestart (FILE *input_file)

Immediately switch to a different input stream.

void yy_switch_to_buffer (YY_BUFFER_STATE new_buffer)

Switch to a different input buffer.

YY_BUFFER_STATE yy_create_buffer (FILE *file, int size)

Allocate and initialize an input buffer state.

• void yy_delete_buffer (YY_BUFFER_STATE b)

Destroy the buffer.

• void yy_flush_buffer (YY_BUFFER_STATE b)

Discard all buffered characters.

void yypush_buffer_state (YY_BUFFER_STATE new_buffer)

Pushes the new state onto the stack.

void yypop_buffer_state (void)

Removes and deletes the top of the stack, if present.

• YY_BUFFER_STATE yy_scan_buffer (char *base, yy_size_t size)

Setup the input buffer state to scan directly from a user-specified character buffer.

YY_BUFFER_STATE yy_scan_string (yyconst char *yystr)

Setup the input buffer state to scan a string.

YY_BUFFER_STATE yy_scan_bytes (yyconst char *yybytes, yy_size_t _yybytes_len)

Setup the input buffer state to scan the given bytes.

FILE * yyget_in (void)

Get the input stream.

void yyset_in (FILE *in_str)

Set the input stream.

FILE * yyget_out (void)

Get the output stream.

yy_size_t yyget_leng (void)

Get the length of the current token.

char * yyget_text (void)

Get the current token.

int yyget_lineno (void)

Get the current line number.

void yyset_lineno (int line_number)

Set the current line number.

Variables

static size_t yy_buffer_stack_top = 0

index of top of stack.

• static size_t yy_buffer_stack_max = 0

capacity of stack.

static YY_BUFFER_STATE * yy_buffer_stack = 0

Stack as an array.

int do_hex = 0

Created and declared by flex.

· long yyval

Use externs from an include file! The flex-generated code is a bit messy.

• YY_DECL

The main scanner function which does all the work.

9.29.1 Detailed Description

This file is to be used instead of the dynamically generated t2mflex.c if there is no flex program installed or if the installed flex is old [e.g 2.5.35 as opposed to 2.5.39 (!)].

Library midicvt application

Author(s) Chris Ahlstrom and many other authors

Date 2014-04-09

Last Edits 2015-08-14

Version

\$Revision\$ License GNU GPL

By using this file, we don't have to use flex again to generate t2mflex.c from t2mf.fl and put up with warning messages.

Of course, you will have to manually, reconstruct the current file if you decided to change the parsing dictated by the t2mf.fl file, or edit Makefile.am to re-enable the use of flex.

Change Note ca 2015-08-14 We want to support "MThd" as an alternative to "MFile" in parsing an ASCII file, so we modified t2mf.fl to also return "MTHD" when encounterding "MThd". Then we rebuilt this module, which was quite a task, even with the help of gvimdiff! Compare the test files in the "results" directory: ex1-mthd.asc versus ex1.asc.

9.29.2 Function Documentation

9.29.2.1 YY_BUFFER_STATE yy_create_buffer (FILE * file, int size)

Allocate and initialize an input buffer state.

Parameters

file	A readable stream.
size	The character buffer size in bytes. When in doubt, use YY_BUF_SIZE.

Returns

the allocated buffer state.

Definition at line 2051 of file t2m_no_flex.c.

9.29.2.2 void yy_delete_buffer (YY_BUFFER_STATE b)

Destroy the buffer.

Parameters

b	a buffer created with yy_create_buffer()

Definition at line 2079 of file t2m no flex.c.

9.29.2.3 void yy_flush_buffer (YY_BUFFER_STATE b)

Discard all buffered characters.

On the next scan, YY_INPUT will be called.

Parameters

b	the buffer state to be flushed, usually YY_CURRENT_BUFFER.

Definition at line 2126 of file t2m_no_flex.c.

9.29.2.4 YY_BUFFER_STATE yy_scan_buffer (char * base, yy_size_t size)

Setup the input buffer state to scan directly from a user-specified character buffer.

Parameters

base	the character buffer

size the size in bytes of the character buffer
--

Returns

the newly allocated buffer state object.

Definition at line 2253 of file t2m no flex.c.

9.29.2.5 YY_BUFFER_STATE yy_scan_bytes (yyconst char * yybytes, yy_size_t _yybytes_len)

Setup the input buffer state to scan the given bytes.

The next call to yylex() will scan from a copy of bytes.

Parameters

yybytes	the byte buffer to scan
_yybytes_len	the number of bytes in the buffer pointed to by bytes.

Returns

the newly allocated buffer state object.

Definition at line 2303 of file t2m_no_flex.c.

9.29.2.6 YY_BUFFER_STATE yy_scan_string (yyconst char * yystr)

Setup the input buffer state to scan a string.

The next call to yylex() will scan from a copy of str.

Parameters

yystr	a NUL-terminated string to scan

Returns

the newly allocated buffer state object.

Note

If you want to scan bytes that may contain NUL values, then use yy_scan_bytes() instead.

Definition at line 2290 of file t2m no flex.c.

9.29.2.7 void yy_switch_to_buffer (YY_BUFFER_STATE new_buffer)

Switch to a different input buffer.

Parameters

new_buffer	The new input buffer.

Definition at line 2006 of file t2m_no_flex.c.

9.29.2.8 void yypop_buffer_state (void)

Removes and deletes the top of the stack, if present.

The next element becomes the new top.

Definition at line 2185 of file t2m_no_flex.c.

9.29.2.9 void yypush_buffer_state (YY_BUFFER_STATE new_buffer)

Pushes the new state onto the stack.

The new state becomes the current state. This function will allocate the stack if necessary.

Parameters

new_buffer | The new state.

Definition at line 2155 of file t2m_no_flex.c.

9.29.2.10 void yyrestart (FILE * input_file)

Immediately switch to a different input stream.

Parameters

input_file A readable stream.

Note

This function does not reset the start condition to ${\tt INITIAL}$.

Definition at line 1987 of file t2m_no_flex.c.

9.29.2.11 void yyset_in (FILE * *in_str*)

Set the input stream.

This does not discard the current input buffer.

Parameters

in_str | A readable stream.

See also

yy_switch_to_buffer

Definition at line 2420 of file t2m no flex.c.

9.29.2.12 void yyset_lineno (int line_number)

Set the current line number.

Parameters

line number

Definition at line 2408 of file t2m_no_flex.c.

9.29.3 Variable Documentation

9.29.3.1 int do_hex = 0

Created and declared by flex.

We added these declarations here to avoid warnings and errors. Find these variables in the flex-generated file t2mflex.c.

Definition at line 1008 of file t2m_no_flex.c.

9.29.3.2 YY_BUFFER_STATE* yy_buffer_stack = 0 [static]

Stack as an array.

Definition at line 316 of file t2m_no_flex.c.

9.29.3.3 size_t yy_buffer_stack_max = 0 [static]

capacity of stack.

Definition at line 315 of file t2m_no_flex.c.

9.29.3.4 size_t yy_buffer_stack_top = 0 [static]

index of top of stack.

Definition at line 314 of file t2m_no_flex.c.

9.29.3.5 long yyval


Use externs from an include file! The flex-generated code is a bit messy.

The generated t2mflex.c file defines these variables, we declare them in t2fm.h, and have to define yyval here. Bleh. Definition at line 89 of file midicvt_globals.c.


9.30 t2mf.h File Reference

This module provides global variables for the text-to-MIDI conversion portion of libmidifilex.

#include <midifilex.h>
Include dependency graph for t2mf.h:



This graph shows which files directly or indirectly include this file:



Macros

#define YY_TYPEDEF_YY_SIZE_T

Good old CentOS's version of flex declared yyleng as an integer.

• #define MTHD 256

Macros galore.

Variables

· int do hex

Created and declared by flex.

· long yyval

Use externs from an include file! The flex-generated code is a bit messy.

9.30.1 Detailed Description

This module provides global variables for the text-to-MIDI conversion portion of libmidifilex.

Library libmidifilex

Author(s) Chris Ahlstrom and many other authors

Date 2014-04-09

Last Edits 2014-04-20

Version

\$Revision\$ License GNU GPL

9.30.2 Macro Definition Documentation

9.30.2.1 #define YY_TYPEDEF_YY_SIZE_T

Good old CentOS's version of flex declared yyleng as an integer.

Debian unstable's flex declares it as yy_size_t. Unfortunately, there's no header-file that defines it! We found one typedef via a web search, but the actual type is a generated typedef in the generated C file, so we have to match that, and hold off the compiler from complaining about a duplicate typedef.

Definition at line 79 of file t2mf.h.

9.30.3 Variable Documentation

9.30.3.1 int do_hex

Created and declared by flex.

We added these declarations here to avoid warnings and errors. Find these variables in the flex-generated file t2mflex.c.

Definition at line 950 of file lex.yy.c.

9.30.3.2 long yyval

Use externs from an include file! The flex-generated code is a bit messy.

The generated t2mflex.c file defines these variables, we declare them in t2fm.h, and have to define yyval here. Bleh. Definition at line 89 of file midicvt_globals.c.

9.31 VERSION.h File Reference

This module provides simpler version information for the libmidifilex library.

9.31.1 Detailed Description

This module provides simpler version information for the libmidifilex library.

Library libmidifilex

Author(s) Chris Ahlstrom

Date 2007-02-28

Last Edits 2014-06-02

Version

\$Revision\$ License GNU GPL

Index

o CCNALLAN	Fields
~csvarray midipp::csvarray, 10	midipp::csvarray, 10
~initree	filegetc
midipp::initree, 16	midicvt_base.c, 54
~stringmap	midicvt_m2m.c, 86
midipp::stringmap, 35	fileputc
	midicvt_m2m.c, 86
active	find
midipp::midimapper, 26	midipp::initree, 17
badbyte	midipp::stringmap, 36
midifilex.c, 112	get16val
begin	midicvt_base.c, 55
midipp::initree, 16, 17	getbyte
midipp::stringmap, 35	midicvt_base.c, 55
biggermsg	getint
midifilex.c, 112	midicvt_base.c, 55
	gs_have_input_file
chanmessage	midicvt_helpers.c, 80
midifilex.c, 112	gs_have_output_file
check_option	midicvt_helpers.c, 80
midicvt_helpers.c, 78 midicvt_helpers.h, 82	gs_help_usage_1
checkchan	midicvt_helpers.c, 80
midicvt_base.c, 54	gs_help_version midicvt_helpers.c, 81
const iterator	gs_input_file
midipp::initree, 15	midicvt_helpers.c, 81
Container	gs_output_file
midipp::initree, 15	midicvt_helpers.c, 81
midipp::stringmap, 34	gs_singleton_midimapper
csvarray	midimapper.cpp, 133
midipp::csvarray, 10	
csvarray.cpp, 38	ininames.hpp, 41
show, 39	initree
TOKEN_SPACES, 39	midipp::initree, 16 initree.cpp, 43
csvarray.hpp, 39 show, 41	show, 45
3110W, 41	initree.hpp, 45
do hex	show, 46
t2m_no_flex.c, 145	iniwriting.cpp, 47
t2mf.h, 147	iniwriting.hpp, 48
drum_map	insert
midipp::midimapper, 26	midipp::initree, 18
	midipp::stringmap, 36
empty	is_comment
midipp::csvarray, 10	midipp::csvarray, 11
midipp::initree, 17 midipp::stringmap, 35	midipp::initree, 18
end	iterator
midipp::initree, 17	midipp::initree, 15
midipp::stringmap, 35	m2m_arbitrary
eputc eputc	midicvt_m2m.c, 86
midifilex.c, 113	m2m_chanpressure
error	midicvt_m2m.c, 87
midicvt_base.c, 54	midicvt_m2m.h, 98
midicvt_base.h, 71	m2m_error

midicvt_m2m.c, 87 m2m header	midipp::midimapper, 30 m_gm_channel
midicvt_m2m.c, 87	midipp::midimapper, 31
m2m_keysig	m_is_valid
midicvt_m2m.c, 88	midipp::csvarray, 12
m2m meot	m_map_reversed
midicvt_m2m.c, 88	midipp::midimapper, 31
m2m mmisc	m_map_type
midicvt_m2m.c, 89	midipp::midimapper, 31
m2m mseq	m_patch_map
midicvt_m2m.c, 89	midipp::midimapper, 31
m2m_mspecial	m_record_count
midicvt_m2m.c, 90	midipp::midimapper, 31
m2m mtext	m sections
midicvt_m2m.c, 90	midipp::initree, 21
m2m_noff	m_separator
midicvt_m2m.c, 91	midipp::csvarray, 12
midicvt_m2m.h, 98	m_setup_name
m2m_non	midipp::midimapper, 32
midicvt_m2m.c, 91	MFILE_FORMAT_4
midicvt_m2m.h, 99	midicvt_base.c, 54
m2m_parameter	MIDI_NOTE_MIN
midicvt_m2m.c, 92	midicvt_macros.h, 103
midicvt_m2m.h, 99	MIDICVT_PATH_MAX
m2m_pitchbend	midicvt_helpers.c, 78
midicvt_m2m.c, 93	main
midicvt_m2m.h, 100	midicvt_main.c, 105
m2m_pressure	midicvtpp_main.cpp, 10
midicvt_m2m.c, 93	mainpage-reference.dox, 49
midicvt_m2m.h, 100	make_section
m2m_program	midipp::initree, 18
midicvt_m2m.c, 93	metaevent
midicvt_m2m.h, 101	midifilex.c, 113
m2m_smpte	mf_sec2ticks
midicvt_m2m.c, 94	midifilex.c, 114
m2m_sysex	midifilex.h, 125
midicvt_m2m.c, 94	mf_ticks2sec
m2m_tempo	midifilex.c, 114
midicvt_m2m.c, 95	midifilex.h, 125
m2m_timesig	mf_w_header_chunk
midicvt_m2m.c, 95	midifilex.c, 115
m2m_trend	midifilex.h, 126
midicvt_m2m.c, 96	mf_w_meta_event
m2m_trstart	midifilex.c, 115
midicvt_m2m.c, 96	midifilex.h, 126
m_Name	mf_w_midi_event
midipp::stringmap, 38	midifilex.c, 115
m_channel_map	midifilex.h, 126
midipp::midimapper, 30	mf_w_tempo
m_csv_lines	midifilex.c, 116
midipp::csvarray, 12	midifilex.h, 127
m_device_channel midipp::midimapper, 30	mf_w_track_chunk midifilex.c, 116
	midifilex.h, 127
m_drum_map midipp::midimapper, 30	mf_w_track_start
m_file_style	midifilex.c, 117
midipp::midimapper, 30	midifilex.h, 128
m_filter_channel	mferror

midifilex.c, 117	midicvt_base.h, 69
mfread	error, 71
midifilex.c, 117	midicvt_compile, 71
midifilex.h, 128	midicvt_setup_compile, 71
mfreport	midicvt_setup_mfread, 71
midifilex.c, 117	midicvt_compile
mfreportable	midicvt_base.c, 55
midifilex.c, 117	midicvt_base.h, 71
mftransform	midicvt_globals.c, 72
midifilex.c, 117	midicvt_option_compile, 73
midifilex.h, 128	midicvt_option_m2m, 73
mfwrite	yyval, 74
midifilex.c, 118	midicvt_globals.h, 74
midifilex.h, 128	midicvt_option_compile, 76
midi_file_offset	midicvt_option_m2m, 76
midicvt_helpers.c, 79	READMT_EOF, 76
midicvt_helpers.h, 83	yyval, 76
midi_functions.dox, 49	midicvt_help
midicvt_base.c, 49	midicvt_helpers.c, 79
checkchan, 54	midicvt_helpers.h, 83
error, 54	midicvt_helpers.c, 76
filegetc, 54	check_option, 78
get16val, 55	gs_have_input_file, 80
getbyte, 55	gs_have_output_file, 80
getint, 55	gs_help_usage_1, 80
MFILE_FORMAT_4, 54	gs_help_version, 81
midicvt_compile, 55	gs_input_file, 81
midicvt_setup_compile, 55	gs_output_file, 81
midicvt_setup_mfread, 56	MIDICVT_PATH_MAX, 78
my_arbitrary, 56	midi_file_offset, 79
my_chanpressure, 56	midicvt_help, 79
my_error, 56	midicvt_parse, 79
my_header, 58	midicvt_set_input_file, 79
my_keysig, 58	midicvt_set_output_file, 79
my_meot, 59	midicvt_version, 80
my_mmisc, 59	report, 80
my_mseq, 61	midicvt_helpers.h, 81
my_mspecial, 61	check_option, 82
my_mtext, 62	midi_file_offset, 83
my_noff, 62	midicvt_help, 83
my_non, 63	midicvt_parse, 83
my_parameter, 63	midicvt_set_input_file, 83
my_pitchbend, 64	midicvt_set_output_file, 83
my_pressure, 64	midicvt_version, 84
my_program, 64	midicvt_initfuncs_m2m
my_smpte, 65	midicvt_m2m.c, 96
my_sysex, 65	midicvt_m2m.h, 101
my_tempo, 66	midicvt_license.dox, 84
my_timesig, 66	midicvt_m2m.c, 84
my_trend, 67	filegetc, 86
my_trstart, 67	fileputc, 86
my_writetrack, 67	m2m_arbitrary, 86
prhex, 68	m2m_chanpressure, 87
prnote, 68	m2m_error, 87
prs_error, 68	m2m_header, 87
prtext, 68	m2m_keysig, 88
prtime, 69	m2m_meot, 88
redirect_stdout, 69	m2m_mmisc, 89

m2m_mseq, 89	main, 107
m2m_mspecial, 90	midicvtpp_help, 108
m2m_mtext, 90	midicvtpp_parse, 108
m2m_noff, 91	s_help_version, 108
m2m_non, 91	s_ini_in_filename, 108
m2m_parameter, 92	s_mapping_name, 108
m2m_pitchbend, 93	s_write_csv_drum, 109
m2m_pressure, 93	s_write_csv_patch, 109
m2m_program, 93	midicvtpp_parse
m2m_smpte, 94	midicvtpp_main.cpp, 108
m2m_sysex, 94	midifile
m2m_tempo, 95	midifilex.c, 118
m2m_timesig, 95	midifilex.h, 129
m2m_trend, 96	midifilex.c, 109
m2m_trstart, 96	badbyte, 112
midicvt_initfuncs_m2m, 96	biggermsg, 112
midicvt_m2m.h, 97	chanmessage, 112
m2m_chanpressure, 98	eputc, 113
m2m_noff, 98	metaevent, 113
m2m_non, 99	mf_sec2ticks, 114
m2m_parameter, 99	mf_ticks2sec, 114
m2m_pitchbend, 100	mf_w_header_chunk, 115
m2m_pressure, 100	mf_w_meta_event, 115
m2m_program, 101	mf_w_midi_event, 115
midicvt_initfuncs_m2m, 101	mf_w_tempo, 116
midicvt_macros.h, 101	mf_w_track_chunk, 116
MIDI_NOTE_MIN, 103	mf_w_track_start, 117
not_nullptr, 103	mferror, 117
nullptr, 103	mfread, 117
midicvt_main.c, 104	mfreport, 117
main, 105	mfreportable, 117
midicvt_option_compile	mftransform, 117
midicvt_globals.c, 73	mfwrite, 118
midicvt_globals.h, 76	midifile, 118
midicvt_option_m2m	msg, 118
midicvt_globals.c, 73	msgadd, 118
midicvt_globals.h, 76	msgleng, 119
midicvt_parse	read16bit, 119
midicvt_helpers.c, 79	read32bit, 119
midicvt_helpers.h, 83	readheader, 119
midicvt_set_input_file	readmt, 119
midicvt_helpers.c, 79	readtrack, 120
midicvt_helpers.h, 83	readtrack_m2m, 120
midicvt_set_output_file	readvarinum, 121
midicvt_helpers.c, 79	s_chantype, 122
midicvt_helpers.h, 83	s_message_buffer, 123
midicvt setup compile	s track header offset, 123
midicvt_base.c, 55	sysex, 121
midicvt_base.h, 71	to16bit, 121
midicvt setup mfread	to32bit, 121
midicvt base.c, 56	write16bit, 122
midicvt_base.h, 71	write32bit, 122
midicvt version	writevarinum, 122
midicvt_helpers.c, 80	midifilex.h, 123
midicvt_helpers.h, 84	mf sec2ticks, 125
midicvtpp_help	mf_ticks2sec, 125
midicvtpp_main.cpp, 108	mf w header chunk, 126
midicvtpp_main.cpp, 105	mf_w_meta_event, 126
πισιοντρρ_παιπ.ορρ, του	iii_vv_iiicta_cvciit, 120

and an anieli arrant 100	namet itamatau 45
mf_w_midi_event, 126	const_iterator, 15
mf_w_tempo, 127	Container, 15
mf_w_track_chunk, 127	empty, 17
mf_w_track_start, 128	end, 17
mfread, 128	find, 17
mftransform, 128	initree, 16
mfwrite, 128	insert, 18
midifile, 129	is_comment, 18
note_off, 125	iterator, 15
write32bit, 129	m_sections, 21
midimap_chanpressure	make_section, 18
midimapper.cpp, 131	operator=, 19
midimap_init	process_option, 19
midimapper.cpp, 131	process_section_name, 19
midimapper.hpp, 135	readfile, 20
midimap_noff	Section, 16
midimapper.cpp, 131	section, 20, 21
midimap non	size, 21
midimapper.cpp, 131	sm_dummy_section, 21
midimap parameter	midipp::midimapper, 21
midimapper.cpp, 132	active, 26
midimap_patch	drum_map, 26
•	_ ·
midimapper.cpp, 132	m_channel_map, 30
midimap_pitchbend	m_device_channel, 30
midimapper.cpp, 132	m_drum_map, 30
midimap_pressure	m_file_style, 30
midimapper.cpp, 133	m_filter_channel, 30
midimapper	m_gm_channel, 31
midipp::midimapper, 24	m_map_reversed, 31
midimapper.cpp, 129	m_map_type, 31
gs_singleton_midimapper, 133	m_patch_map, 31
midimap_chanpressure, 131	m_record_count, 31
midimap_init, 131	m_setup_name, 32
midimap_noff, 131	midimapper, 24
midimap_non, 131	read_channel_section, 26
midimap_parameter, 132	read_maps, 28
midimap_patch, 132	read_unnamed_section, 28
midimap_pitchbend, 132	rechannel, 28
midimap pressure, 133	repatch, 29
show_maps, 133	repitch, 29
midimapper.hpp, 133	midipp::stringmap
midimap_init, 135	~stringmap, 35
show_maps, 135	begin, 35
midipp::csvarray, 7	Container, 34
~csvarray, 10	empty, 35
csvarray, 10	* *
• •	end, 35
empty, 10	find, 36
Fields, 10	insert, 36
is_comment, 11	m_Name, 38
m_csv_lines, 12	operator=, 37
m_is_valid, 12	size, 37
m_separator, 12	stringmap, 34
operator=, 11	value, 37
readfile, 11	midipp::stringmap< VALUETYPE >, 32
size, 11	midipp_functions.dox, 137
midipp::initree, 12	msg
∼initree, 16	midifilex.c, 118
begin, 16, 17	msgadd

midifilex.c, 118	midipp::initree, 19
msgleng	midipp::stringmap, 37
midifilex.c, 119	
my_arbitrary	prhex
midicvt_base.c, 56	midicvt_base.c, 68
my_chanpressure	prnote
midicvt_base.c, 56	midicvt_base.c, 68
my_error	process_option
midicvt_base.c, 56	midipp::initree, 19
my_header	process_section_name
midicvt_base.c, 58	midipp::initree, 19
my_keysig	prs_error
midicvt_base.c, 58	midicvt_base.c, 68
my_meot	prtext
midicvt_base.c, 59	midicvt_base.c, 68
my_mmisc	prtime
midicvt_base.c, 59	midicvt_base.c, 69
my_mseq	
midicvt base.c, 61	READMT_EOF
my_mspecial	midicvt_globals.h, 76
midicvt_base.c, 61	read16bit
my_mtext	midifilex.c, 119
midicvt_base.c, 62	read32bit
my_noff	midifilex.c, 119
midicvt_base.c, 62	read_channel_section
my_non	midipp::midimapper, 26
midicvt_base.c, 63	read_maps
my_parameter	midipp::midimapper, 28
midicvt_base.c, 63	read_unnamed_section
my_pitchbend	midipp::midimapper, 28
midicvt_base.c, 64	readfile
my_pressure	midipp::csvarray, 11
midicvt_base.c, 64	midipp::initree, 20
my_program	readheader
midicvt_base.c, 64	midifilex.c, 119
	readmt
my_smpte	midifilex.c, 119
midicvt_base.c, 65	readtrack
my_sysex	midifilex.c, 120
midicvt_base.c, 65	readtrack m2m
my_tempo	midifilex.c, 120
midicvt_base.c, 66	readvarinum
my_timesig	midifilex.c, 121
midicvt_base.c, 66	rechannel
my_trend	
midicvt_base.c, 67	midipp::midimapper, 28
my_trstart	redirect_stdout
midicvt_base.c, 67	midicvt_base.c, 69
my_writetrack	repatch
midicvt_base.c, 67	midipp::midimapper, 29
	repitch
not_nullptr	midipp::midimapper, 29
midicvt_macros.h, 103	report
note_off	midicvt_helpers.c, 80
midifilex.h, 125	a chantuna
nullptr	s_chantype
midicvt_macros.h, 103	midifilex.c, 122
	s_help_version
operator=	midicvtpp_main.cpp, 108
midipp::csvarray, 11	s_ini_in_filename

midicvtpp_main.cpp, 108	do_hex, 147
s_mapping_name	YY_TYPEDEF_YY_SIZE_T, 147
midicvtpp_main.cpp, 108	yyval, 147
s_message_buffer	TOKEN_SPACES
midifilex.c, 123	csvarray.cpp, 39
s_track_header_offset	to16bit
midifilex.c, 123	midifilex.c, 121
s_write_csv_drum	to32bit
midicvtpp_main.cpp, 109	midifilex.c, 121
s_write_csv_patch	VEDOLONIA
midicvtpp_main.cpp, 109	VERSION.h, 148
Section	value
midipp::initree, 16	midipp::stringmap, 37
section	writed Chit
midipp::initree, 20, 21	write16bit
show	midifilex.c, 122
csvarray.cpp, 39	write32bit
csvarray.hpp, 41	midifilex.c, 122
initree.cpp, 45	midifilex.h, 129 writevarinum
initree.hpp, 46	
stringmap.cpp, 138	midifilex.c, 122
stringmap.hpp, 140	YY TYPEDEF YY SIZE T
show_maps	t2mf.h, 147
midimapper.cpp, 133	yy_buffer_stack
midimapper.hpp, 135	t2m_no_flex.c, 145
size	yy_buffer_stack_max
midipp::csvarray, 11	t2m_no_flex.c, 145
midipp::initree, 21	yy_buffer_stack_top
midipp::stringmap, 37	t2m_no_flex.c, 146
sm_dummy_section	yy_create_buffer
midipp::initree, 21	t2m_no_flex.c, 142
stringmap	yy_delete_buffer
midipp::stringmap, 34	t2m_no_flex.c, 142
stringmap.cpp, 137	yy_flush_buffer
show, 138	t2m_no_flex.c, 142
stringmap.hpp, 138	yy_scan_buffer
show, 140	t2m_no_flex.c, 142
sysex	yy_scan_bytes
midifilex.c, 121	t2m_no_flex.c, 143
t2m_no_flex.c, 140	yy_scan_string
do hex, 145	t2m_no_flex.c, 143
yy_buffer_stack, 145	yy switch to buffer
yy buffer stack max, 145	t2m_no_flex.c, 143
yy_buffer_stack_top, 146	yypop_buffer_state
yy_create_buffer, 142	t2m_no_flex.c, 143
yy_delete_buffer, 142	yypush_buffer_state
yy_flush_buffer, 142	t2m_no_flex.c, 143
yy_scan_buffer, 142	yyrestart
yy_scan_bytes, 143	t2m_no_flex.c, 145
yy_scan_string, 143	yyset in
yy_switch_to_buffer, 143	t2m_no_flex.c, 145
yypop_buffer_state, 143	yyset_lineno
yypush_buffer_state, 143	t2m_no_flex.c, 145
yyrestart, 145	yyval
yyset_in, 145	midicvt_globals.c, 74
yyset_lineno, 145	midicvt_globals.h, 76
yyval, 146	t2m_no_flex.c, 146
t2mf.h, 146	t2mf.h, 147
Lemmi, 170	,