



PUBLIC

Sample Code Configuration Guide for Integration with SAP Business Network Global Track and Trace

SAP Business Network Global Track and Trace

January 2024

Contents

Document History	3
1. PREREQUISITES	4
1.1 Check the SAP Product Version	4
1.2 Log on the Development Client to Configure BTE	4
2. DOWNLOAD ABAP CODE FROM GITHUB	5
2.1 Initial Download ABAP Code from GitHub	5
2.1.1 <i>Install ABAPGit</i>	5
2.1.2 <i>Download ABAP Code from GitHub</i>	5
2.2 Update ABAP Code from GitHub	7
2.2.1 <i>Update ABAP Code from GitHub</i>	7
3. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 1 (IMPORT BC SET + MANUAL CONFIGURATION)	8
3.1 Download BC Set from GitHub	9
3.2 Import BC Set	10
3.3 Activate BC Set	11
3.4 Define RFC Connection for SAP Business Network Global Track and Trace	14
3.5 Define Ports	18
3.6 Define Partner Profiles	19
3.7 Maintain AOT Type Restriction for Cross-Processes	21
3.8 Maintain Event Type Restriction for Cross-Processes	21
3.9 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace	21
3.10 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace	21
3.11 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace	22
4. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 2 (MANUAL CONFIGURATION)	22
4.1 Define RFC Connection for SAP Business Network Global Track and Trace	22
4.2 Define Logical System	26
4.3 Define Ports	27
4.4 Define Partner Profiles	28
4.5 Define CI tenant for SAP Business Network Global Track and Trace	30
4.6 Define GTT Extraction Functions	30
4.7 Define Used Business Process Types, Appl. Object Types and Event Types	36
4.8 Define Application Object Types for Header Level Extractor	37
4.9 Define Application Object Types for Item Level Extractor	41
4.10 Define Event Types for Header Level Extractor	44
4.11 Define Event Types for Item Level Extractor	46
4.12 Purchase Order Extractor Configuration	48
4.12.1 <i>Define Application Object Types for Purchase Order Header</i>	48
4.12.2 <i>Define Application Object Types for Purchase Order Item</i>	48
4.12.3 <i>Define Event Types for Purchase Order Item</i>	49
4.12.4 <i>Cross-processes for Purchase Order</i>	50
4.12.5 <i>Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace</i>	51
4.13 Inbound Delivery Extractor Configuration	52
4.13.1 <i>Define Application Object Types for Inbound Delivery Header</i>	52
4.13.2 <i>Define Application Object Types for Inbound Delivery Item</i>	53

4.13.3 Define Event Types for Inbound Delivery Header	54
4.13.4 Define Event Types for Inbound Delivery Item.....	54
4.13.5 Cross-processes for Inbound Delivery	55
4.13.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace ..	55
4.14 Sales Order Extractor Configuration	56
4.14.1 Define Application Object Types for Sales Order Header	56
4.14.2 Define Application Object Types for Sales Order Item.....	56
4.14.3 Cross-processes for Sales Order	57
4.14.4 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace ..	57
4.15 Outbound Delivery Extractor Configuration.....	57
4.15.1 Define Application Object Types for Outbound Delivery Header.....	57
4.15.2 Define Application Object Types for Outbound Delivery Item.....	58
4.15.3 Define Event Types for Outbound Delivery Header	59
4.15.4 Define Event Types for Outbound Delivery Item.....	59
4.15.5 Cross-processes for Outbound Delivery	61
4.15.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace ..	61
4.16 Shipment Extractor Configuration	61
4.16.1 Define Application Object Types for Shipment Header.....	61
4.16.2 Define Event Types for Shipment Header.....	62
4.17 Freight Unit Extractor Configuration	64
4.17.1 Define Application Object Types for Freight Unit Header.....	64
4.17.2 Define Event Types for Freight Unit Header	64
4.18 Road Freight Order/Ocean Booking/Air Booking Extractor Configuration	70
4.18.1 Define Application Object Types for Road Freight Order/Ocean booking/Air Booking Header	70
4.18.2 Define Event Types for Road Freight Order/Ocean Booking/Air Booking Header	70
5. CONFIGURATION AND CODING GUIDE – ADVANCED	75
6 KNOWN ISSUES.....	75
6.1 Planned Event Extension Not Enabled.....	75
6.2 One-time locations Relevant	75
APPENDIX ONE: DEFINE THE UNPLANNED EVENTS FOR AIR BOOKING	76
APPENDIX TWO: FAQS	78
Q1: After the configuration of GTT and SAP TM systems, we found that the freight unit / freight order / freight booking IDOC cannot be sent to SAP Business Network Global Track and Trace, how can we do the troubleshooting?	78
Q2: How to add customized planned event and synchronize this event back to SAP TM?	86
Q3: How to update business partner's LBN ID?	89
Q4: How is the connection established between SAP S/4HANA and SAP Business Network Global Track and Trace? Do I need to configure PI in SAP S/4HANA?	89
Q5: What scenarios are supported in SAP Business Network Global Track and Trace?	90
Q6: Do sample codes support one-time locations? Where can I maintain the one-time location address?	91
Q7: How to stop sending unnecessary IDOCs from SAP S/4HANA to the GTT system?	92
Q8: How to deactivate or activate the application log?	92

Document History

2401 Release:

1. Update the document title to "Sample Code Configuration Guide for Integration with SAP Business Network Global Track and Trace"

2307 Release:

2. Update [3.3 Activate BC Set](#)
3. Update [5. Configuration and Coding Guide-Advanced](#)

2306 Release:

1. Update [2.1.1 Install ABAPGit](#)
2. Update [2.1.2 Download ABAP Code from GitHub](#)
3. Update [3.7 Maintain AOT Type Restriction for Cross-Processes](#)
4. Update [3.8 Maintain Event Type Restriction for Cross-Processes](#)
5. Update [4.12.4 Cross-processes for Purchase Order](#)
6. Update [4.13.5 Cross-processes for Inbound Delivery](#)
7. Update [4.14.3 Cross-processes for Sales Order](#)
8. Update [4.15.5 Cross-processes for Outbound Delivery](#)

2305 Release:

1. Update [3.4 Define RFC Connection for SAP Business Network Global Track and Trace](#)
2. Update [4.1 Define RFC Connection for SAP Business Network Global Track and Trace](#)
3. Update [5.7 Enhancement Codes for Cross-processes Tracking](#)
4. Add [Q8: How to deactivate or activate the application log?](#)

2304 Release:

1. Update prerequisites for Chapter 3 SAP S/4HANA Integration Configuration option 1 (Import BC set + Manual configuration)
2. Update [5.7 Enhancement Codes for Cross-processes Tracking](#)
3. Add the [Chapter 6 Known Issues](#)
4. Update [Q1: After the configuration of GTT and SAP TM systems, we found that the freight unit / freight order / freight booking IDOC cannot be sent to SAP Business Network Global Track and Trace, how can we do the troubleshooting?](#)
5. Add the following FAQs:
 - [Q6: Do sample codes support one-time locations? Where can we maintain the one-time location address?](#)
 - [Q7: How to stop sending unnecessary IDOCs from SAP S/4HANA system to the GTT system?](#)

2303 Release:

1. Update [3.4 Define RFC Connection for SAP Business Network Global Track and Trace](#)
2. Update [3.7 Maintain AOT Type Restriction for Cross-Processes](#)
3. Update [3.10 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace](#)
4. Add [3.11 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace](#)
5. Update [4.1 Define RFC Connection for SAP Business Network Global Track and Trace](#)
6. Update [4.12.4 Cross-processes for Purchase Order](#)
7. Add [4.12.5 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace](#)
8. Add [4.13.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace](#)
9. Update [4.14.3 Cross-processes for Sales Order](#)
10. Update [Q2: How to add customized planned event and synchronize this event back to SAP TM?](#)
11. Add [Q4: How is the connection established between SAP S/4HANA and SAP Business Network Global Track and Trace? Do we need to configure PI in SAP S/4HANA?](#)
12. Add [Q5: What scenarios are supported in SAP Business Network Global Track and Trace?](#)

1. PREREQUISITES

1.1 Check the SAP Product Version

Make sure that you have met the requirements for the product version mentioned in the “[Prerequisites](#)” section of *Basic Knowledge: Connect to SAP S/4HANA* in *How to Send Documents from SAP S/4HANA to SAP Business Network Global Track and Trace*. You can find this guide at <http://help.sap.com/gtt>.

The ABAP codes on Github to support fulfillment tracking apps for SAP Business Network Global Track and Trace shall be implemented in SAP S/4HANA 1909 SP03 on premise or higher. Please note that the codes are not validated in its lower version or other ECC series of products, so you might need to do further adaptation work or build your own extractor.

1.2 Log on the Development Client to Configure BTE

- 1.2.1 Ensure you have development access to the client for cross-client customizing and local development.
- 1.2.2 Log on to the client and enter transaction code (T-code): **FIBF**.
- 1.2.3 Click **More->Settings -> Identification -> SAP Applications**.
- 1.2.4 Position on the Application ID: **PI-EM**. Check the field Application Active.

Appl.	A	Text
<input type="checkbox"/>	<input checked="" type="checkbox"/>	SAP Event Manager Integration
<input type="checkbox"/>	<input checked="" type="checkbox"/>	PIX Payment
<input type="checkbox"/>	<input checked="" type="checkbox"/>	Instandhaltung
<input type="checkbox"/>	<input checked="" type="checkbox"/>	Instandhaltung-BW
<input type="checkbox"/>	<input checked="" type="checkbox"/>	Instandhaltung, Equipment

- 1.2.5 Click **Save**.

2. DOWNLOAD ABAP CODE FROM GITHUB


2.1 Initial Download ABAP Code from GitHub

2.1.1 Install ABAPGit

You need to install ABAPGit before downloading the codes from GitHub. To install ABAPGit, follow the instructions on <https://docs.abapgit.org/user-guide/getting-started/install.html>. Make sure you **Install the standalone version** in your dev system. When installation is complete, a new report is created, **ZABAPGIT_STANDALONE**.

2.1.2 Download ABAP Code from GitHub

2.1.2.1 Enter T-code **SE38** and fill in the report name from [2.1.1](#), **ZABAPGIT_STANDALONE**. Click **Execute** to run the report.



2.1.2.2 Click **New Online** to download the code.

A screenshot of the abapGit application's "Tutorial" section. At the top, there's a navigation bar with "abapGit" and "Tutorial" buttons, and links for "Repository List", "New Online" (which is highlighted with a purple border), "New Offline", "Settings", and help. The main content area has a heading "Tutorial" and a "Online repositories" section with a bulleted list: "To clone a remote repository (e.g. from github) click New Online from the top menu. This will link a remote repository with a package on your system.", "Use the pull button to retrieve and activate the remote objects.", and "If the remote repository is updated, you will see the changes and can pull to apply the updates." Below that is an "Offline repositories" section with a bulleted list: "To add a package as an offline repository, click New Offline from the top menu.", "abapGit will start tracking changes for the package without linking it to an online git repository.", and "You can link the package later or just export the package content as a ZIP file." At the bottom is a "Repository list and favorites" section with a bulleted list: "To favorite a repository, use the ★ icon in the repository list.", "To go to a repository, click on the repository name.", "To go back to your favorites, use the Repository List", and "Explore to find projects using abapGit".

2.1.2.3 Fill in the **Git Repository URL**.

<https://github.com/SAP-samples/logistics-business-network-gtt-standardapps-samples.git>

2.1.2.4 Fill in the **Package** where you want to create the new ABAP code. If the package does not exist yet, click **Create package** to create it. Set **Full** for **Folder Logic**. Click **Clone Online Repo** to download the code.

abapGit

abapGit ► New Online Repository

Git Repository URL *

Package *

Branch

Folder Logic

Prefix

Display Name

Ignore Subpackages

Serialize Main Language Only

2.1.2.5 Assign the change to a change request. If you do not have any available change requests, you need to create a new one.

2.1.2.6 Click **Pull** to pull down the code of the latest version.

The screenshot shows the abapGit interface with the following details:

- Repository:** GTT-V2-Standard-Apps (<https://SAP-samples/logistics-business-network-gtt-standardapps-samples.git>)
- Branch:** master
- Actions:** Pull, Stage, Diff, Branch, Tag, Advanced, View, Refresh
- Table Headers:** Type, Name, Path
- Table Data:**
 - Type: CLAS
 - Name: ZCL_GTT_MIA_AE_FILLER_DLH_GR, ZCL_GTT_MIA_AE_FILLER_DL_PKA, ZCL_GTT_MIA_AE_FILLER_DL_PKN, ZCL_GTT_MIA_AE_FILLER_DLH_BH, ZCL_GTT_MIA_AE_FILLER_SHH_BS, ZCL_GTT_MIA_AE_PARAMETERS, ZCL_GTT_MIA_AE_PERFORMER, ZCL_GTT_MIA_AE_PROCESSOR, ZCL_GTT_MIA_CTP_DAT_TOR_TO_DLH, ZCL_GTT_MIA_CTP_DAT_TOR_TO_DL, ZCL_GTT_MIA_CTP_SHIPMENT_DATA, ZCL_GTT_MIA_CTP SND, ZCL_GTT_MIA_CTP SND SH_TO_DLH
 - Path: /abapgit.xml, /bin/gt-standard-app/abap/zsrc/zgtt_mia/zcl_gtt_mia_ae_filler_dlh_gr.clas.abap, /bin/gt-standard-app/abap/zsrc/zgtt_mia/zcl_gtt_mia_ae_filler_dlh_gr.clas.xml, ... (many more paths listed)
 - Actions: diff (for each item)

2.1.2.7 After you download the code, you can check it with T-code **SE80**.

2.2 Update ABAP Code from GitHub

In each release, there are some changes in the public sample codes. To update your local sample codes of Fulfillment Tracking apps after a future release, do the following:

2.2.1 Update ABAP Code from GitHub

2.2.1.1 Enter T-code **SE38** and fill in the report name **ZABAPGIT_STANDALONE**. Click the **Execute** icon to run the report.

The screenshot shows the SAP ABAP Editor: Initial Screen with the following details:

- Program:** ZABAPGIT_STANDALONE
- Buttons:** Create, Debugging, With Variant, Variants, More
- Subobjects:**
 - Source code (radio button selected)
 - Variants
 - Attributes
 - Text elements
 - Documentation


2.2.1.2 To access the Fulfillment Tracking apps' repository, click the button.

2.2.1.3 Click **Pull** to pull down the latest version code.

3. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 1 (IMPORT BC SET + MANUAL CONFIGURATION)

Prerequisites:

- For this option, you must establish the system environment WITHOUT a production client for preparation. If you try to import the BC set into the system with a production client, an error will pop up.



Performance Assistant

BC Sets cannot be activated in production systems; see the long text

Message no. SCPR229

Diagnosis

You tried to activate BC Sets in a system with at least one production client. This is not allowed. You can only activate Business Configuration Sets in systems with no production client.

System Response

The procedure was cancelled. No data was written into customizing tables.

Procedure

Activate the BC Set in a test system.

- You must maintain the business process types used for SAP Business Network Global Track and Trace correctly. To do so, follow the steps below:
 - In **Display IMG** page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface**.
 - Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types**.
 - Choose **Define Used Business Process Types** and click **New Entries** to maintain business process type as follows:

Business Process Type	Update Mode	BPT Processing Mode	Description
ESC_DELIV	Update Task (V1)	Active	Delivery in SAP R/3 Enterprise
ESC_MATDOC	Update Task (V1)	Active	Material Document in SAP R/3 Enterprise
ESC_PURORD	Update Task (V1)	Active	Purchase Order in SAP R/3 Enterprise

ESC_SHIPMT	Update Task (V1)	Active	Shipment (SAP R/3 Enterprise)
ESC_SORDER	Update Task (V1)	Active	Sales Order in SAP R/3 Enterprise
TMS_TOR	Update Task (V1)	Active	Transportation Order (SAP TM)

3.1 Download BC Set from GitHub

3.1.1 Navigate to BC Set in https://github.com/SAP-samples/logistics-business-network-gtt-standardapps-samples/blob/main/lbn-gtt-standard-app/BCset/ZGTT_CONF.bcs.

3.1.2 Click on “Raw” button.


The screenshot shows the GitHub interface for the SAP-samples / logistics-business-network-gtt-standardapps-samples repository. The main navigation bar includes 'Search or jump to...', 'Pull requests', 'Issues', 'Marketplace', and 'Explore'. Below the repository name, it says 'generated from SAP-samples/apache2-reuse-template'. The top right corner has a 'Watch' button. The main content area shows the 'Code' tab selected, followed by 'Issues', 'Pull requests', 'Actions', 'Projects', 'Security', and 'Insights'. A dropdown menu for the 'main' branch is open. The repository path is listed as 'logistics-business-network-gtt-standardapps-samples / lbn-gtt-standard-app / BCset / ZGTT_CONF.bcs'. On the right, there are buttons for 'Go to file' and three dots. Below this, a box contains the commit 'i067300 initial version' with a timestamp of 'Latest commit 318@cc5 12 hours ago' and a 'History' link. It also shows '0 contributors'. At the bottom, a table lists repository details: 1191 lines (1191 sloc), 444 KB, and a blame link. The table rows are:

1	VERSION	1
2	DATE	20210513
3	BCSET	ZGTT_CONF
4	ORGID	/CUSTOMER/
5	COMPONENT	SAP_BASIS
6	HEIRENRELEASE	750
7	MAINTCLASS	

3.1.3 Click **Save as** to save the configuration file to your local path.

raw.githubusercontent.com/SAP-samples/logistics-business-network-gtt-standard-app/main/lbn-gtt-standard-app/BCSet/ZGTT_CONF.bcs?token=ASES7yJFVHZ3Ne4463Oy2DAU3IDY


3.1.4 Change file extension to “.bcs”.




3.2 Import BC Set

3.2.1 From SAP Easy Access Menu, **Tools -> Customizing -> Business Configuration Sets -> Display and Maintain BC Sets** (Transaction Code SCPR3).

3.2.2 Select Upload BC Set.



3.2.3 Select the file " ZGTT_CONF.bcs", then click **Open** to upload the BC set to your development system.



All of the configurations are loaded in the system.

The screenshot shows the SAP Business Configuration Sets: Change interface. The top bar displays the title "Business Configuration Sets: Change". The left sidebar has a "No Favorites List" and a search bar. The main area shows "BC Set ID: ZGTT_CONF" and "Short Text: GTT Standard APP Configuration". A tree view under "GTT Standard APP Configuration (ZGTT_CONF)" includes nodes for "Define Logical System", "Define Used Business Process Types, Appl. Object Ty", "Define SAP GTT Extraction Functions", and "Define CI Tenant for SAP GTT". To the right, there's a section titled "Tables and Views for Selected Customizing Object" showing "Table/View" and "Text" for "V_TBDLS" (Logical Systems). Below this is a table titled "Data Records" with a single entry "GTTAPPLOGS" (Logical System for GTT Standard APP). A message bar at the bottom says "BC Set ZGTT_CONF saved".

3.2.4 Click **Save** to save the BC Set.

BC Set ZGTT_CONF saved

3.3 Activate BC Set

3.3.1 From SAP Easy Access Menu, **Tools** -> **Customizing** -> **Business Configuration Sets** -> **Activation of BC Sets** (Transaction Code SCPR20).

3.3.2 Enter the name of the BC Set and select **Activate**.

The screenshot shows the SAP Business Configuration Sets: Activation interface. The top bar displays the title "Business Configuration Sets: Activation". The main area has fields for "BC Set:" (containing "ZGTT_CONF") and "Short Text:" (containing "GTT Standard APP Configuration"). A toolbar with various icons is visible above the input fields.

3.3.3 Provide a Workbench request and a Customizing request.

Prompt for Workbench request

Request: 900368 Workbench request

Short Description: Import GTT Standard APP configuration

Own Requests

Prompt for Customizing request

Request: 900372 Customizing request



Short Description: Import GTT Standard APP configuration

Own Requests

3.3.4 Various activation options are available. Choose appropriate ones and click **Continue** to proceed with the activation.

The following message is displayed:

Caution You have started the BC Set activation If you continue, new data records will be created and/or existing ones overwritten."



3.3.5 BC Set is activated and BC set data is stored in the customization tables.

The screenshot shows two SAP application windows. The top window is titled "Business Configuration Sets: Activation" and displays a warning message: "Activation ended with warning" with a link to "View details". The bottom window is titled "Business Configuration Sets: Activation Logs" and shows the activation log for BC Set "ZGTT_CONF". The log details various activation events and messages, such as "Main Activation Started" and "User-defined languages are not installed in the system".

Tips:

By default, the application log is activated for the imported configurations. If you want to stop recording the application log, refer to [Q8: How to deactivate or activate the application log?](#) for detailed instructions.

3.4 Define RFC Connection for SAP Business Network Global Track and Trace

3.4.1 Log on to the business client, enter T-code **SPRO** and then click **SAP Reference IMG** to open **Display IMG** page.

3.4.2 Click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define System Configuration**. Choose activity: **Define RFC Connection for SAP GTT**

3.4.3 Choose **HTTP Connections to External Server**, click **Create** to create a new RFC connection.

SAP Configuration of RFC Connections

Generate RFC Callback Allowlist Activate Non-Empty Allowlists Allowlist for Dynamic

● OO RFC callback check not secure

RFC Connections	Type	PL Active	Comment
> ABAP Connections	3		
> HTTP Connections to External Server	G		
> HTTP Connections to ABAP System	H		
> Internal Connections	I		
> Logical Connections	L		

3.4.4 Fill in the **Destination** and choose the **Connection Type**: “G-HTTP connection to external server”.

Create Destination

* Destination: GTT_APP_RFC

* Connection Type: G HTTP connection to external server

3.4.5 Enter a description. In the **Technical Settings** tab, fill in the **Host**, **Port** and **Path Prefix**.

For example, the URL of solution owners is as follows:

<https://xxxxxx.gtt-flp-lbnplatform-pre-live.cfapps.eu10.hana.ondemand.com/>

Host: xxxx.gtt-flp-lbnplatform-pre-live.cfapps.eu10.hana.ondemand.com

Port: 443

Path Prefix: /api/idoc/em/v1/TrackedProcessAndEvent

The screenshot shows the SAP Fiori launchpad interface. At the top, there is a blue header bar with the SAP logo and a back arrow icon. Below the header, the title "RFC Destination GTT_APP_RFC" is displayed. On the left, there is a search bar and a "Connection Test" button. To the right of the search bar, there is a "More" dropdown menu.

The main content area contains the following fields:

- RFC Destination:** GTT_APP_RFC
- Connection Type:** G (selected) - HTTP Connection to External Server
- Description:** A section for additional descriptive text, containing three empty input fields labeled "Description 1", "Description 2", and "Description 3".

At the bottom of the screen, there is a navigation bar with tabs: Administration, **Technical Settings** (which is highlighted with a purple border), Logon & Security, and Special Options.

In the center, under "Target System Settings", there are two input fields:

- Host:** (empty input field)
- Port:** 443


Below these fields, there is another input field for the **Path Prefix:** /api/idoc/em/v1/TrackedProcessAndEvent, which is also highlighted with a purple border.

3.4.6 In the **Logon & Security** tab, enter the Logon information.

For the basic authentication, the GTT technical user / password is needed. You can get this from your GTT administrator.

For more information about the technical user, please refer to "[Create a Technical User and Assign Role Collection](#)".

Also, SSL must be **Active**. The recommended SSL Certificate is: DEFAULT SSL Client (Standard).




The screenshot shows the SAP Fiori interface for configuring an RFC destination. The top navigation bar includes the SAP logo and the title "RFC Destination GTT_APP_RFC". Below the title, there are buttons for "Connection Test" and "More". The main configuration area starts with "RFC Destination: GTT_APP_RFC" and "Connection Type: G HTTP Connection to External Server". A "Description" section follows, containing three fields: "Description 1: RFC for GTT Standard APP", "Description 2:", and "Description 3:". At the bottom of this section is a "Special Options" button. The "Logon & Security" tab is currently selected, indicated by a purple border. The "Logon Procedure" section contains two sub-sections: "Logon with User" (selected) and "Logon with Ticket". The "Logon with User" section has radio buttons for "Do not use a user" (unchecked) and "Basic authentication" (checked), with a "User:" field containing "saved" and an "OAuth Settings" button. The "Logon with Ticket" section has radio buttons for "Do not send logon ticket" (checked), "Send ticket without reference to target system", and "Send assertion ticket for dedicated target system". It also includes "System ID" and "Client" input fields. The "Logon with MQTT/AMQP" section contains a "User:" field and a "PW Status:" field showing "is initial". The "Security Options" section includes a "Status of Secure Protocol" group with "SSL" radio buttons for "Inactive" (unchecked) and "Active" (checked), a "SSL Certificate" dropdown set to "DEFAULT SSL Client (Standard)", a "Cert. List" dropdown, and a checkbox for "Do not use certificate for logon".

3.4.7 Save the configuration.

3.4.8 Click **Connection Test** and check the HTTP status code in the **Test Result** tab:

- Status code “403” indicates the configuration is correct. No action is required.
- If the status code is “401” or a prompt window (as shown in the screenshot below) appears asking your username and password, there are two possibilities:
 - The technical user is locked (informed by an email received in the technical user’s mailbox), you need to follow the steps in the email to unlock the technical user.
 - Your username, password, or URL of **Host** and **Path Prefix** is incorrect. You need to provide the correct ones.



3.5 Define Ports


3.5.1 In **Display IMG** page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> IDoc Settings**. Choose activity **Define Ports**.

3.5.2 Choose **XML HTTP** folder, and click **Create** to create a new port **GTTAPPORT**.

3.5.3 Fill in the **RFC Destination**.

3.5.4 Choose **Content Type** as *application/x-sap.idoc*

3.5.5 Choose **HTTP Version** as Version 1.0. Mark it as **SOAP Protocol**.



3.5.6 Save the configuration.

3.6 Define Partner Profiles

3.6.1 In Display IMG page, unfold Integration with Other SAP Components -> Interface to Global Track and Trace -> IDoc Settings. Choose activity Define Partner Profiles.

3.6.2 Choose Partner Type LS folder, and click Create to create a new partner profile.

The screenshot shows the SAP Fiori interface for defining partner profiles. On the left, there is a tree view under 'Partner Profiles' with various partner types listed: Partner Type AD, Partner Type B (Bank), Partner Type BP (Benefits provider), Partner Type GP (Business Partner), Partner Type KU (Customer), Partner Type LI (Vendor), Partner Type LS (Logical system), and Partner Type US (User). The 'Partner Type LS' node is selected and highlighted with a purple border. On the right, there is a form for creating a new partner profile. The 'Partner No.' field contains 'GTTAPPLOGS' and the 'Type' field contains 'LS'. Below the form, tabs for 'Post Processing: Valid Processors', 'Classification', and 'Telephony' are visible. Under 'Post Processing: Valid Processors', fields for 'Ty.' (set to 'US'), 'Processor' (empty), and 'Lang.' (set to 'EN') are shown. The 'Processor' field is also highlighted with a purple border.

3.6.3 Fill in the **Partner No.** that you created and fill in the **Processor** information.

This screenshot shows the 'Post Processing: Valid Processors' tab for the partner profile 'GTTAPPLOGS'. The 'Ty.' field is set to 'US', the 'Processor' field is empty, and the 'Lang.' field is set to 'EN'. The 'Processor' field is highlighted with a purple border. Below the tab, there is an 'Outbound' section containing a table with columns: Partner Role, Message Type, Message Variant, Function, Test, Receiver Port, I..., Pac..., and Basic Type. There are three rows in the table, each with an empty 'Message Type' column. At the bottom of the table, there are icons for search, add, and delete.

3.6.4 Click **Add** under **Outbound** box to create a new outbound parameter.

This screenshot shows the 'Outbound' section of the partner profile configuration. The table has columns: Partner Role, Message Type, Message Variant, Function, Test, Receiver Port, I..., Pac..., and Basic Type. There are three rows in the table, all of which have an empty 'Message Type' column. At the bottom of the table, there are icons for search, add, and delete. The 'Add' icon (a plus sign) is highlighted with a purple border.

3.6.5 Fill in the Message Type GTTMSG and Fill in the Receiver Port that you created in [3.5](#).

The screenshot shows the SAP Fiori interface for configuring Partner profiles: Outbound parameters. The page title is "Partner profiles: Outbound parameters". The partner details section includes:

- Partner No.: **GTTAPPLOGS** (Logical System for GTT Standard APP)
- Type: **LS** (Logical system)
- Partner Role:

The message type section shows:

- Message Type: **GTTMSG**
- Message Code:
- Message Function:
- Test

The outbound options section includes:

- Outbound Options (selected)
- Message Control
- Post Processing: Valid Processors
- Telephony
- EDI Standard

The receiver port section shows:

- Receiver Port: **GTTAPPOR** (Port for GTT Standard APP)
- Pack. Size: **0**
- Queue Processing

The output mode section shows:

- Pass IDoc Immediately
- Collect IDocs

The output mode value is **2**.

The IDoc type section shows:

- Basic Type: **GTTMSG01** (LBN-TT: Process and Event Posting)
- Extension:
- View:
- Cancel Processing After Syntax Error
- Seg. release in IDoc type:
- Application Release:

3.6.6 Save the configuration.

3.7 Maintain AOT Type Restriction for Cross-Processes

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for Cross-Processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
FU_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
FU_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT
SH_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
SH_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT
DL_TO_POIT	001	Equal To	Include	GTT_PO_IT
DL_TO_SOIT	001	Equal To	Include	GTT_SO_IT
SH_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLI	001	Equal To	Include	GTT_ODLV_IT
DL_TO_POHD	001	Equal To	Include	GTT_PO_HD
DL_TO_SOHD	001	Equal To	Include	GTT_SO_HD

3.8 Maintain Event Type Restriction for Cross-Processes

The following entry should be maintained in transaction “ZGTT_EVTYPE_RST – Event Types Restrictions” for Cross-Processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Event Type
DL_TO_POIT	001	Equal To	Include	GTT_EVT_PO_IT_CF

3.9 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the sales order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_SOTYPE_RST - GTT Sales Doc Type Configuration”, then mark it as active.

For example:

Sales Document Type	Active
ZGTT	X

3.10 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace

Maintain the outbound and inbound delivery type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_DLVTYPE_RST - GTT Delivery Type Configuration”, then mark it as active.

For example:

Delivery Type	Active
LBNP	X
EL	X

3.11 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the purchase order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_POTYPE_RST - GTT Purchase Doc Type Configuration”, then mark it as active.

For example:

Purchasing Document Type	Active
NB	X

4. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 2 (MANUAL CONFIGURATION)

4.1 Define RFC Connection for SAP Business Network Global Track and Trace

4.1.1 Log on to the business client, enter T-code **SPRO** and then click **SAP Reference IMG** to open **Display IMG** page.

4.1.2 Click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define System Configuration**. Choose activity: **Define RFC Connection for SAP GTT**

4.1.3 Choose **HTTP Connections to External Server**. Click **Create** to create a new RFC connection.

Configuration of RFC Connections

●OO RFC callback check not secure

	RFC Connections	Type	PL Active	Comment
<input type="checkbox"/>	> ABAP Connections	3		
<input type="checkbox"/>	> HTTP Connections to External Server	G		
<input type="checkbox"/>	> HTTP Connections to ABAP System	H		
<input type="checkbox"/>	> Internal Connections	I		
<input type="checkbox"/>	> Logical Connections	L		

4.1.4 Fill in the **Destination** and choose the **Connection Type**: 'G-HTTP connection to external server'.

Create Destination

* Destination: GTT_APP_RFC

* Connection Type: G HTTP connection to external server

✓ ✗

4.1.5 Enter a description. In the **Technical Settings** tab, fill in the **Host**, **Port** and **Path Prefix**.

For example, the URL of solution owners is as follows:

<https://xxxxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com>

Host: xxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com

Port: 443

Path Prefix: /api/idoc/em/v1/TrackedProcessAndEvent

The screenshot shows the SAP Fiori launchpad interface. A modal dialog is open for configuring an RFC destination named "GTT_APP_RFC". The "Technical Settings" tab is selected. In the "Target System Settings" section, the "Host" field contains "xxxxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com" and the "Port" field contains "443". The "Path Prefix" field contains "/api/idoc/em/v1/TrackedProcessAndEvent". The "Connection Type" is set to "HTTP Connection to External Server". The "Description" section includes three descriptive lines: "Description 1: RFC for GTT Standard APP", "Description 2: ", and "Description 3: ". Navigation tabs at the bottom include "Administration", "Technical Settings" (selected), "Logon & Security", and "Special Options".

4.1.6 In the **Logon & Security** tab, enter the Logon information.

For the basic authentication, the GTT technical user / password is needed. You can get this from your GTT administrator.

For more information about the technical user, please refer to "[Create a Technical User and Assign Role Collection](#)".

Also, SSL must be **Active**. The recommended SSL Certificate is: DEFAULT SSL Client (Standard).

The screenshot shows the SAP Fiori interface for configuring an RFC destination. The top navigation bar includes the SAP logo and the title "RFC Destination GTT_APP_RFC". Below the title, there are tabs for "Connection Test" and "More". The main configuration area has the following fields:

- RFC Destination:** GTT_APP_RFC
- Connection Type:** G HTTP Connection to External Server
- Description:** (This section contains three empty text input fields labeled "Description 1", "Description 2", and "Description 3".)

Below the configuration area, there is a navigation bar with tabs: Administration, Technical Settings, **Logon & Security**, and Special Options. The "Logon & Security" tab is highlighted with a purple border.


The "Logon & Security" tab contains several sections:

- Logon Procedure:**
 - Logon with User:** The "Basic authentication" option is selected. It includes fields for "User" (empty) and "PW Status" (saved).
 - Logon with Ticket:** The "Do not send logon ticket" option is selected. It includes a "System ID" field and two empty input fields for "Client" and "Target".
 - Logon with MQTT/AMQP:** It includes fields for "User" (empty) and "PW Status" (is initial).
- Security Options:**
 - Status of Secure Protocol:** The "SSL" dropdown is set to "Active". The "SSL Certificate" dropdown is set to "DEFAULT SSL Client (Standard)". A checkbox for "Do not use certificate for logon" is unchecked.

4.1.7 Save the configuration.

4.1.8 Click **Connection Test** and check the HTTP status code in the **Test Result** tab:

- Status code “403” indicates the configuration is correct. No action is required.
- If the status code is “401” or a prompt window (as shown in the screenshot below) appears asking your username and password, there are two possibilities:
 - The technical user is locked (informed by an email received in the technical user’s mailbox), you need to follow the steps in the email to unlock the technical user.
 - Your username, password, or URL of **Host** and **Path Prefix** is incorrect. You need to provide the correct ones.



4.2 Define Logical System

4.2.1 In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define System Configuration**. Choose activity **Define Logical System**.

4.2.2 Create **New Entries** to create a new Logical System, fill in the Logical System code and Name of the new logical system.

Logical Systems	
Log.System	Name
GTTAPPLOGS	Logical System for GTT Standard APP

4.2.3 Save the configuration.

4.3 Define Ports


4.3.1 In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> IDoc Settings**. Choose activity **Define Ports**.

4.3.2 Choose **XML HTTP** folder, and click **Create** to create a new port **GTTAPPPORT**.

4.3.3 Fill in the **RFC Destination**.

4.3.4 Choose **Content Type** as *application/x-sap.idoc*

4.3.5 Choose **HTTP Version** as Version 1.0. Mark it as SOAP Protocol.



4.3.6 Save the configuration.

4.4 Define Partner Profiles

4.4.1 In Display IMG page, unfold Integration with Other SAP Components -> Interface to Global Track and Trace -> IDoc Settings. Choose activity Define Partner Profiles.

4.4.2 Choose Partner Type LS folder, and click Create to create a new partner profile.

The screenshot shows the SAP Fiori interface for managing partner profiles. On the left, there is a tree view under 'Partner Profiles' with various categories like Partner Type AD, B, BP, GP, KU, LI, LS, and US. The 'Partner Type LS' node is selected and highlighted with a purple border. To the right, there are several input fields and tabs. The 'Post Processing: Valid Processors' tab is active. It contains fields for 'Partner No.' (with placeholder 'GTTAPPLOGS'), 'Type' (with placeholder 'LS'), 'Ty.:' (with placeholder 'US'), 'Processor' (with placeholder 'User'), and 'Lang.' (with placeholder 'EN'). There are also tabs for 'Classification' and 'Telephony'. At the bottom, there is a table titled 'Outbound' with columns for Partner Role, Message Type, Message Variant, Function, Test, Receiver Port, I..., Pac..., and Basic Type. The first few rows of the table are visible.

4.4.3 Fill in the Partner No. that you created and fill in the Processor information.

This screenshot provides a detailed view of the partner profile creation screen. The 'Post Processing: Valid Processors' tab is still active. The 'Partner No.' field contains 'GTTAPPLOGS' and has a tooltip 'Logical System for GTT Standard APP'. The 'Type' field contains 'LS'. Below these, the 'Ty.:' field contains 'US' (highlighted with a purple border), the 'Processor' field contains 'User', and the 'Lang.' field contains 'EN' (highlighted with a purple border). The 'Classification' and 'Telephony' tabs are also visible. At the bottom, there is a table for 'Outbound' settings with columns for Partner Role, Message Type, Message Variant, Function, Test, Receiver Port, I..., Pac..., and Basic Type. The first few rows of the table are visible.

4.4.4 Click **Add** under the **Outbound** box to create a new outbound parameter.

Partner No.: **GTTAPPLOGS** Logical System for GTT Standard APP
Type: **LS** Logical system

Post Processing: Valid Processors Classification Telephony

Ty.: **US** User
Processor:
Lang.: **EN** English

Outbound

Partner Role	Message Type	Message Variant	Function	Test	Receiver Port	I...	Pac...	Basic Type
(empty)	(empty)	(empty)	(empty)	<input type="checkbox"/>	(empty)	(empty)	(empty)	(empty)
(empty)	(empty)	(empty)	(empty)	<input type="checkbox"/>	(empty)	(empty)	(empty)	(empty)
(empty)	(empty)	(empty)	(empty)	<input type="checkbox"/>	(empty)	(empty)	(empty)	(empty)

+ Add

4.4.5 Fill in the Message Type GTTMSG and Fill in the Receiver Port that you created in [4.3](#).

Partner profiles: Outbound parameters

Partner No.: **GTTAPPLOGS** Logical System for GTT Standard APP
Type: **LS** Logical system
Partner Role:

Message Type: **GTTMSG**
Message Code:
Message Function: Test

Outbound Options Message Control Post Processing: Valid Processors Telephony EDI Standard

Receiver Port: **GTTAPPOR** Port for GTT Standard APP
Pack. Size: **0**
 Queue Processing

Output Mode
 Pass IDoc Immediately Output Mode: 2
 Collect IDocs

IDoc Type
Basic Type: **GTTMSG01** LBN-TT: Process and Event Posting
Extension:
View:
 Cancel Processing After Syntax Error
Seg. release in IDoc type: Application Release:

4.4.6 Save the configuration.

4.5 Define CI tenant for SAP Business Network Global Track and Trace

4.5.1 In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface**.

Choose activity **Define CI Tenant for SAP GTT**.

4.5.2 Click **New Entries** to create a new CI tenant for SAP Business Network Global Track and Trace, fill in the information for the new CI tenant. The **CI Log. System** is the logical system you created in [4.2](#).

The top screenshot shows the 'Change View "SAP Global Track & Trace Definitions": Overview' screen. A purple box highlights the 'New Entries' button in the toolbar. The bottom screenshot shows the 'Display View "SAP Global Track & Trace Definitions": Overview' screen, where a new entry 'GTTAPPLOGS' has been created. The 'Description' column for this entry contains the text 'CI Tenant for GTT Standard APP'.

4.6 Define GTT Extraction Functions

Prerequisite:

You have already installed ABAPGit and downloaded the code of Fulfillment Tracking apps in your development system.

4.6.1 In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface**. Choose activity **Define SAP GTT Extraction Functions**.

4.6.2 Choose the type of extraction function you want to create from the **Dialog Structure**, and click **New entries**.

The screenshot shows the 'Change View "GTT Relevance Functions (App. Obj. Types)": Overview' screen. A purple box highlights the 'New entries' button in the toolbar. On the left, the 'Dialog Structure' sidebar lists several categories under 'GTT Relevance Functions (App. Obj. Types)'. The 'Function' table on the right is currently empty, showing columns for 'Function', 'Function Module', and 'Description'.

4.6.3 Input the **Function name** and **Function Module** for the newly created extraction function.

The screenshot shows the SAP Fiori interface for defining GTT relevance functions. On the left, there's a sidebar titled 'Dialog Structure' with several categories like 'GTT Relevance Functions (App. Obj. Types)', 'GTT Relevance Functions (Event Types)', etc. The main area is titled 'GTT Relevance Functions (App. Obj. Types)' and contains a table with three columns: 'Function', 'Function Module', and 'Description'. One row is selected, highlighted with a purple background: 'GTT_MIA_IDLV_HD_REL' in the Function column, 'ZGTT_MIA_OTE_DL_HDR_REL' in the Function Module column, and 'Appl. Object Type Relevance for Inbound Delivery Header' in the Description column.

4.6.4 Click **Save**.

Hint:

After completing the configuration of 'Define GTT Extraction Functions', the configuration should be as follows:

Category	Extractor	Function Module Name	Description
Control Parameter Extractors	GTT_MIA_IDLV_HD_OTE	ZGTT_MIA_OTE_DL_HDR	Control Parameter Extractor for Inbound Delivery Header
	GTT_MIA_IDLV_IT_OTE	ZGTT_MIA_OTE_DL_ITEM	Control Parameter Extractor for Inbound Delivery Item
	GTT_MIA_SHP_HD_OTE	ZGTT_MIA_OTE_SH_HDR	Control Parameter Extractor for Shipment Header
	GTT_TS_FO_HD_OTE	ZGTT_STS_OTE_FO_HDR	Control Parameter Extractor for Freight Order and Freight Booking
	GTT_TS_FU_HD_OTE	ZGTT_STS_OTE_FO_HDR	Control Parameter Extractor for Freight Unit
	GTT_POF_PO_HD_OTE	ZGTT_SPOF_OTE_PO_HDR	Control Parameter Extractor for Purchase Order Header
	GTT_POF_PO_IT_OTE	ZGTT_SPOF_OTE_PO_ITM	Control Parameter Extractor for Purchase Order Item
	GTT_SOF_SO_HD_OTE	ZGTT_SSOF_OTE_SO_HD	Control Parameter Extractor for Sales Order Header
	GTT_SOF_SO_IT_OTE	ZGTT_SSOF_OTE_SO_ITEM	Control Parameter Extractor for Sales Order Item
	GTT_SOF_ODLV_HD_OTE	ZGTT_SSOF_OTE_DE_HD	Control Parameter Extractor for Outbound Delivery Header
Event Data Extractors	GTT_SOF_ODLV_IT_OTE	ZGTT_SSOF_OTE_DE_ITEM	Control Parameter Extractor for Outbound Delivery Item
	GTT_MIA_IDLV_HD_GR	ZGTT_MIA_EE_DL_HDR_GR	Actual event Inbound Delivery Header Goods Receipt

	GTT_MIA_IDLV_IT_PA	ZGTT_MIA_EE_DL_ITEM_PA	Actual event Inbound Delivery Item Put Away
	GTT_MIA_IDLV_IT_PKNG	ZGTT_MIA_EE_DL_ITEM_PKNG	Actual event Inbound Delivery Item Packing
	GTT_MIA_SHP_HD_ARR	ZGTT_MIA_EE_SH_HDR_ARR	Actual event Shipment Header Arrival
	GTT_MIA_SHP_HD_CI	ZGTT_MIA_EE_SH_HDR_CI	Actual event Shipment Header Check In
	GTT_MIA_SHP_HD_DEP	ZGTT_MIA_EE_SH_HDR_DEP	Actual event Shipment Header Departure
	GTT_MIA_SHP_HD_LE	ZGTT_MIA_EE_SH_HDR_LE	Actual event Shipment Header Load End
	GTT_MIA_SHP_HD_LS	ZGTT_MIA_EE_SH_HDR_LS	Actual event Shipment Header Load Start
	GTT_TS_TOR_ARRIVAL	ZGTT_STS_EE_FO_ARRIVAL	Actual Event FO/FB/FU Proof of Arrival
	GTT_TS_TOR_COUPLING	ZGTT_STS_EE_FO_COUPLING	Actual Event FO/FB/FU Coupling
	GTT_TS_TOR_DECOUPL	ZGTT_STS_EE_FO_DECOUPLING	Actual Event FO/FB/FU Decoupling
	GTT_TS_TOR_DELAY	ZGTT_STS_EE_FO_DELAY	Actual Event FO/FB/FU Delay
	GTT_TS_TOR_DEPART	ZGTT_STS_EE_FO_DEPARTURE	Actual Event FO/FB/FU Proof of Departure
	GTT_TS_TOR_FU_DELAY	ZGTT_STS_EE_FU_DELAY	Actual Event FO/FB/FU Delay
	GTT_TS_TOR_LOAD_END	ZGTT_STS_EE_FO_LOAD_END	Actual Event FO/FB/FU Loading End
	GTT_TS_TOR_LOAD_STR	ZGTT_STS_EE_FO_LOAD_START	Actual Event FO/FB/FU Loading Start
	GTT_TS_TOR_POD	ZGTT_STS_EE_FO_POD	Actual Event FO/FB/FU Proof of Delivery
	GTT_TS_TOR_POPU	ZGTT_STS_EE_FO_POPU	Actual Event FO/FB/FU Proof of Pick-Up
	GTT_TS_TOR_UNLD_END	ZGTT_STS_EE_FO_UNLOAD_END	Actual Event FO/FB/FU Unloading End
	GTT_TS_TOR_UNLD_STR	ZGTT_STS_EE_FO_UNLOAD_START	Actual Event FO/FB/FU Unloading Start
	GTT_POF_PO_IT_CF	ZGTT_SPOF_EE_PO_ITM_CONF	Actual Event PO Item Confirmation
	GTT_POF_PO_IT_DE	ZGTT_SPOF_EE_PO_ITM_DEL	Actual Event PO Item Deletion
	GTT_POF_PO_IT_GR	ZGTT_SPOF_EE_PO_ITM_GR	Actual Event PO Item Goods Receipt
	GTT_SOF_ODLV_GI	ZGTT_SSOF_EE_DE_GI	Actual Event of Outbound Delivery Goods Issue
	GTT_SOF_ODLV_IT_PA	ZGTT_SSOF_EE_DE_PACKING	Actual Event Outbound Delivery Packing
	GTT_SOF_ODLV_IT_PI	ZGTT_SSOF_EE_DE_PICKING	Actual Event Outbound Delivery Picking
	GTT_SOF_ODLV_IT_POD	ZGTT_SSOF_EE_DE_POD	Actual Event Outbound Delivery POD
Planned Event Extractors	GTT_MIA_IDLV_HD_EE	ZGTT_MIA_EE_DL_HDR	Selection of EEs for Inbound Delivery Header
	GTT_MIA_IDLV_IT_EE	ZGTT_MIA_EE_DL_ITEM	Selection of EEs for Inbound Delivery Item

	GTT_MIA_SHP_HD_EE	ZGTT_MIA_EE_SH_HDR	Selection of EEs for Shipment Header
	GTT_TS_FO_HD_EE	ZGTT_STS_EE_FO_HDR	Selection of EEs for FO/FB Header
	GTT_TS_FU_HD_EE	ZGTT_STS_EE_FO_HDR	Selection of EEs for FU Header
	GTT_POF_PO_HD_EE	ZGTT_SPOF_EE_PO_HDR	Selection of EEs for Purchase Order Header
	GTT_POF_PO_IT_EE	ZGTT_SPOF_EE_PO_ITM	Selection of EEs for Purchase Order Item
	GTT_SOF_SO_HD_EE	ZGTT_SSOF_EE_SO_HD	Selection of EEs for Sales Order Header
	GTT_SOF_SO_IT_EE	ZGTT_SSOF_EE_SO_ITM	Selection of EEs for Sales Order Item
	GTT_SOF_ODLV_HD_EE	ZGTT_SSOF_EE_DE_HD	Selection of EEs for Outbound Delivery Header
	GTT_SOF_ODLV_IT_EE	ZGTT_SSOF_EE_DE_ITM	Selection of EEs for Outbound Delivery Item
Tracking ID Extractors	GTT_MIA_IDLV_HD_TID	ZGTT_MIA_OTE_DL_HDR_TID	Tracking ID Extractor for Inbound Delivery Header
	GTT_MIA_IDLV_IT_TID	ZGTT_MIA_OTE_DL_ITEM_TID	Tracking ID Extractor for Inbound Delivery Item
	GTT_MIA_SHP_HD_TID	ZGTT_MIA_OTE_SH_HDR_TID	Tracking ID Extractor for Shipment Header
	GTT_TS_FO_HD_TID	ZGTT_STS_OTE_FO_HEADER_TID	Tracking ID Extractor for Freight Order and Freight Booking
	GTT_TS_FU_HD_TID	ZGTT_STS_OTE_FO_HEADER_TID	Tracking ID Extractor for Freight Unit
	GTT_POF_PO_HD_TID	ZGTT_SPOF_OTE_PO_HDR_TID	Tracking ID Extractor for Purchase Order Header
	GTT_POF_PO_IT_TID	ZGTT_SPOF_OTE_PO_ITM_TID	Tracking ID Extractor for Purchase Order Item
	GTT_SOF_SO_HD_TID	ZGTT_SSOF_TRACKID_OTE_SOHDR	Tracking ID Extractor for Sales Order Header
	GTT_SOF_SO_IT_TID	ZGTT_SSOF_TRACKID_OTE_SOITEM	Tracking ID Extractor for Sales Order Item
	GTT_SOF_ODLV_HD_TID	ZGTT_SSOF_TRACKID_OTE_DEHDR	Tracking ID Extractor for Outbound Delivery Header
GTT relevance function of AOT	GTT_SOF_ODLV_IT_TID	ZGTT_SSOF_TRACKID_OTE_DEITEM	Tracking ID Extractor for Outbound Delivery Item
	GTT_MIA_IDLV_HD_REL	ZGTT_MIA_OTE_DL_HDR_REL	Appl. Object Type Relevance for Inbound Delivery Header
	GTT_MIA_IDLV_IT_REL	ZGTT_MIA_OTE_DL_ITEM_REL	Appl. Object Type Relevance for Inbound Delivery Item
	GTT_MIA_SHP_HD_REL	ZGTT_MIA_OTE_SH_HDR_REL	Appl. Object Type Relevance for Shipment Header

GTT relevance function of Event Type	GTT_TS_FO_HD_REL	ZGTT_STS_OTE_FO_HDR_REL	Appl. Object Type Relevance for FO/FB Header
	GTT_TS_FU_HD_REL	ZGTT_STS_OTE_FO_HDR_REL	Appl. Object Type Relevance for FU Header
	GTT_POF_PO_HD_REL	ZGTT_SPOF_OTE_PO_HDR_REL	Appl. Object Type Relevance for Purchasing Order Header
	GTT_POF_PO_IT_REL	ZGTT_SPOF_OTE_PO_ITM_REL	Appl. Object Type Relevance for Purchasing Order Item
	GTT_SOF_SO_HD_REL	ZGTT_SSOF_OTE_SO_HDR_REL	Appl. Object Type Relevance for Sales Order Header
	GTT_SOF_SO_IT_REL	ZGTT_SSOF_OTE_SO_ITM_REL	Appl. Object Type Relevance for Sales Order Items
	GTT_SOF_ODLV_HD_REL	ZGTT_SSOF_OTE_DE_HDR_REL	Appl. Object Type Relevance for Outbound Delivery Header
	GTT_SOF_ODLV_IT_REL	ZGTT_SSOF_OTE_DE_ITM_REL	Appl. Object Type Relevance for Outbound Delivery Items
	GTT_MIA_IDLV_HD_GR	ZGTT_MIA_EE_DL_HDR_GR_REL	Relevance function for Actual event Delivery Header Goods Receipt
	GTT_MIA_IDLV_IT_PA	ZGTT_MIA_EE_DL_ITEM_PA_REL	Relevance function for Actual event Delivery Item Put Away
	GTT_MIA_IDLV_IT_PKNG	ZGTT_MIA_EE_DL_ITEM_PKNG_REL	Relevance function for Actual event Delivery Item Packing
	GTT_MIA_SHP_HD_ARR	ZGTT_MIA_EE_SH_HDR_ARR_REL	Relevance function for Actual event Shipment Header Arrival
	GTT_MIA_SHP_HD_CI	ZGTT_MIA_EE_SH_HDR_CI_REL	Relevance function for Actual event Shipment Header Check In
	GTT_MIA_SHP_HD_DEP	ZGTT_MIA_EE_SH_HDR_DEP_REL	Relevance function for Actual event Shipment Header Departure
	GTT_MIA_SHP_HD_LE	ZGTT_MIA_EE_SH_HDR_LE_REL	Relevance function for Actual event Shipment Header Load End
	GTT_MIA_SHP_HD_LS	ZGTT_MIA_EE_SH_HDR_LS_REL	Relevance function for Actual event Shipment Header Load Start
	GTT_TS_TOR_ARRIVE	ZGTT_STS_EE_FO_ARRIVAL_REL	Relevance function for Actual event FO/FB/FU Arrival
	GTT_TS_TOR_COUP	ZGTT_STS_EE_FO_COUPLING_REL	Relevance function for Actual event FO/FB/FU Coupling
	GTT_TS_TOR_DECP	ZGTT_STS_EE_FO_DECOUPLING_REL	Relevance function for Actual event FO/FB/FU Decoupling

	GTT_TS_TOR_DELAY	ZGTT_STS_EE_FO_DELAY_REL	Relevance function for Actual event FO/FB/FU Delay
	GTT_TS_TOR_DEPART	ZGTT_STS_EE_FO_DEPARTURE_REL	Relevance function for Actual event FO/FB/FU Departure
	GTT_TS_TOR_FU_DELAY	ZGTT_STS_EE_FU_DELAY_REL	Relevance function for Actual event FO/FB/FU Freight Unit Delay
	GTT_TS_TOR_LEND	ZGTT_STS_EE_FO_LOAD_END_REL	Relevance function for Actual event FO/FB/FU Loading End
	GTT_TS_TOR_LSTR	ZGTT_STS_EE_FO_LOAD_START_REL	Relevance function for Actual event FO/FB/FU Loading Start
	GTT_TS_TOR_POD	ZGTT_STS_EE_FO_POD_REL	Relevance function for Actual event FO/FB/FU Proof of Delivery
	GTT_TS_TOR_POPU	ZGTT_STS_EE_FO_POPU_REL	Relevance function for Actual event FO/FB/FU Proof of Pick Up
	GTT_TS_TOR_UEND	ZGTT_STS_EE_FO_UNLOAD_END_REL	Relevance function for Actual event FO/FB/FU Unloading End
	GTT_TS_TOR_USTR	ZGTT_STS_EE_FO_UNLOAD_STRT_REL	Relevance function for Actual event FO/FB/FU Unloading Start
	GTT_POF_PO_IT_CF_REL	ZGTT_SPOF_EE_PO_ITM_CONF_REL	Relevance function for Actual event PO Item Confirmation
	GTT_POF_PO_IT_DE_REL	ZGTT_SPOF_EE_PO_ITM_DEL_REL	Relevance function for Actual event PO Item Deletion
	GTT_POF_PO_IT_GR_REL	ZGTT_SPOF_EE_PO_ITM_GR_REL	Relevance function for Actual event PO Item Goods Receipt
	GTT_SOF_ODLV_GI_REL	ZGTT_SSOF_EE_DE_GI_REL	Relevance function for Actual event Outbound Delivery Goods Issue
	GTT_SOF_ODLV_PA_REL	ZGTT_SSOF_EE_DE_PACKING_REL	Relevance function for Actual event Outbound Delivery Packing
	GTT_SOF_ODLV_PI_REL	ZGTT_SSOF_EE_DE_PICKING_REL	Relevance function for Actual event Outbound Delivery Picking
	GTT_SOF_ODLV POD_REL	ZGTT_SSOF_EE_DE_POD_REL	Relevance function for Actual event Outbound Delivery POD
AOID Extractor	GTT_MIA_IDLV_HD_AOID	ZGTT_MIA_AOID_DL_HDR	AOID Extractor for Inbound Delivery Header
	GTT_MIA_IDLV_IT_AOID	ZGTT_MIA_AOID_DL_ITEM	AOID Extractor for Inbound Delivery Item
	GTT_MIA_SHP_HD_AOID	ZGTT_MIA_AOID_SH_HDR	AOID Extractor for Shipment Header
	GTT_STS_AOID_TOR	ZGTT_STS_AOID_TOR	AOID Extractor for FU/FO/FB
	GTT_POF_PO_IT_AOID	ZGTT_SPOF_AOID_PO_ITM	AOID Extractor for Purchase Order Item

GTT_POF_PO_HD_AOID	ZGTT_SPOF_AOID_PO_HDR	AOID Extractor for Purchase Order Header
GTT_SOF_AOID	ZGTT_SSOF_AOID	AOID Extractor for Sales Order / Outbound Delivery

4.7 Define Used Business Process Types, Appl. Object Types and Event Types

4.7.1 In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface.**

Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types.**

4.7.2 You can create event types and application object types for each business process type.

The following sections from 4.8 to 4.11 only demonstrate how to configure relevant objects. For actual configuration, refer to the scenarios configuration listed below.

Scenarios configuration:

1) Purchase Order -> Inbound Delivery -> Shipment.

For this scenario, see the following configurations:

- [4.12](#) Purchase Order Extractor Configuration
- [4.13](#) Inbound Delivery Extractor Configuration
- [4.16](#) Shipment Extractor Configuration

2) Purchase Order -> Inbound Delivery -> Freight Unit -> Road Freight Order / Ocean booking / Air Booking.

For this scenario, see the following configurations:

- [4.12](#) Purchase Order Extractor Configuration
- [4.13](#) Inbound Delivery Extractor Configuration
- [4.17](#) Freight Unit Extractor Configuration
- [4.18](#) Road Freight Order/Ocean Booking/Air booking Extractor Configuration

3) Sales Order -> Outbound Delivery -> Shipment.

For this scenario, see the following configurations:

- [4.14](#) Sales Order Extractor Configuration
- [4.15](#) Outbound Delivery Extractor Configuration
- [4.16](#) Shipment Extractor Configuration

4) Sales Order -> Outbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.

For this scenario, see the following configurations:

- [4.14](#) Sales Order Extractor Configuration
- [4.15](#) Outbound Delivery Extractor Configuration
- [4.17](#) Freight Unit Extractor Configuration
- [4.18](#) Road Freight Order/Ocean Booking/Air Booking Extractor Configuration

4.8 Define Application Object Types for Header Level Extractor

4.8.1 As an example of AOT type's header level tracking introduction, choose the business process type ESC_DELIV from the **Define Used Business Process Types** on the right side.

Double click **Define Application Object Types**.

Bus. Proc. Type	Update Mode	BPT Process Mode	Description
ESC_DELIV	Update Task (V1)	Active	Delivery in SAP R/3 Enterprise
ESC_FI_CLEARING	Update Task (V1)	Active	FI Clearing in SAP R/3 Enterprise

4.8.2 Click **New Entries** to create a new Application Object Type.

4.8.3 Fill in the **Application Object Type** and **Text** fields.

4.8.4 Fill in the information required in the **General Data** tab. **CI for GTT** is the CI Tenant you created in [4.5](#). Check **GTT Relevant**.

Bus. Proc. Type: ESC_DELIV
Appl. Obj. Type: **GTT_IDLV_HD** ① Extract Inbound Delivery Header information to Global Track and Trace
Text: Inb. Delivery Header

General Data Control Tables Object Identification Global Track & Trace Relevance Parameter Setup


Sequencing / Destination
Seq. No.: 10
CI for GTT: **GTTAPPLOGS** CI Tenant for GTT Standard APP

Business Object Reference
Object Type: **BUS2015** InboundDelivery
BO Setup Fnct.:


Behavior
 GTT Relevant
 Stop AO Determ.
 Appl. Log Deact

Hint:

When you are creating Application Object Type for one Business Process Type, make sure the AOT name must be the same name defined in the corresponding model in the *Manage Models* app in Version 2 of SAP Business Network Global Track and Trace.



4.8.5 Fill in the Main Object table and Master Table in the Control Tables tab.




Note:

If the event type or application object type is on the header level, then you only need to assign the **Main Object Table**.


If the event type or application object type is on the item level, then you need to assign the **Main Object Table** and **Master Table**, and assign the reference between the **Main Object Table** and **Master Table**.

4.8.6 If there is no customized logic to determine the AOT ID, choose **Determine from Field**, and use the key field to fill the AO ID fields. When choosing **Determine by Function**, you must enter the customized information in the AOID function field.



4.8.7 In the **Global Track & Trace Relevance** tab, choose the **GTT Relevance Method** you need.

If you choose the **GTT Relevance Method** as *Check Function*, then you need to define a relevance function according to [4.6](#), and fill in the relevance function name here.




4.8.8 In the **Parameter Setup** tab, choose the **TrkID Method** as you need.

If you choose the **TrkID Method** as *Determine by Function*, then you need to define a tracking ID function according to [4.6](#), and fill in the relevance function name here.

If no customized logic exists, for **TrkID Method** choose *Determine from Field*, then you need to fill the key field and name the Code Set for the AOT.

Fill in the extractor functions for **Control Data, Info Data(optional), Planned Event**.

Click **Save**.



Hint:

In the AOT you maintained, make sure the name of Tracking ID Type is the same name defined in the corresponding process type of the model in the *Manage Models* app in Version 2 of SAP Business Network Global Track and Trace.

If the Tracking ID Type is determined by Field, input the value source field in the Tracking ID field, and the Code Set that refers to the Tracking ID Type for the AOT as below.

4.9 Define Application Object Types for Item Level Extractor

4.9.1 As an example of AOT type's item level tracking introduction, choose the business process type ESC_DELIV from the **Define Used Business Process Types** on the right side. Double click **Define Application Object Types**.

The screenshot shows the SAP AOT interface with the title 'Display View "Define Used Business Process Types": Overview'. On the left, there is a 'Dialog Structure' tree with nodes like 'Define Used Business Process Types' and 'Define Application Object Types'. The main area displays a table titled 'Define Used Business Process Types' with columns: Bus. Proc. Type, Update Mode, BPT Process Mode, and Description. Two entries are listed: 'ESC_DELIV' (selected) with 'Update Task (V1)' mode, 'Active' status, and 'Delivery in SAP R/3 Enterprise' description; and 'ESC_FI_CLEARING' with 'Update Task (V1)' mode, 'Active' status, and 'FI Clearing in SAP R/3 Enterprise' description.

4.9.2 Click **New Entries** to create a new Application Object Type.

4.9.3 Fill in the **Application Object Type** and **Text** fields.

4.9.4 Fill in the information required in the **General Data** tab. **CI for GTT** is the CI Tenant you created in [4.5](#). Check **GTT Relevant**.

The screenshot shows the SAP AOT interface with the title 'Display View "Define Application Object Types": Details'. The 'Dialog Structure' tree on the left shows 'Define Used Business Process Types' and 'Define Application Object Types'. The main area has tabs for 'General Data', 'Control Tables', 'Object Identification', 'Global Track & Trace Relevance', and 'Parameter Setup'. The 'General Data' tab is selected, showing fields for 'Bus. Proc. Type' (ESC_DELIV), 'Appl. Obj. Type' (GTT_IDLV_IT), and 'Text' (Inb. Delivery Item). Below these, under 'Sequencing / Destination', is a section for 'Seq. No.' (10) and 'CI for GTT' (GTTAPPLOGS). Under 'Business Object Reference', it shows 'Object Type' (BUS2015) and 'InboundDelivery'. Under 'Behavior', there is a checked checkbox for 'GTT Relevant' and other options like 'Stop AO Determ.' and 'Appl. Log Deact'.


4.9.5 Fill in the Main Object table and Master Table in the Control Tables tab.

The screenshot shows the SAP Fiori interface for defining application object types. The title bar reads "Display View 'Define Application Object Types': Details". The left sidebar shows "Dialog Structure" with sections for "Define Used Business Process Types", "Define Application Object Types" (which is expanded), and "Define Event Types". The main content area has tabs: General Data, Control Tables (selected), Object Identification, Global Track & Trace Relevance, and Parameter Setup. The "Control Tables" tab contains fields for "Bus. Proc. Type" (ESC_DELIV), "Appl. Obj. Type" (GTT_IDLV_IT) with a description "Extract Inbound Delivery Item information to Global Track and Trace", and "Text" (Inb. Delivery Item). A section titled "Data Source for Created and Updated Objects" contains fields for "Main Obj. Table" (DELIVERY_ITEM_NEW) and "Master Table" (DELIVERY_HEADER_NEW), both highlighted with a purple border. Another section titled "Data Source for Deleted Objects" contains a field for "Del.Obj. Table" (DELIVERY_ITEM_OLD) also highlighted with a purple border. Below these are sections for "Reference Between Main and Master Table" and "Second Field Reference from Main to Master Table", each with uplink fields and mode/const fields, also highlighted with a purple border.


4.9.6 Fill in the AOID method in the Object Identification tab.

The screenshot shows the SAP Fiori interface for defining application object types, focusing on the "Object Identification" tab. The title bar reads "Display View 'Define Application Object Types': Details". The left sidebar shows "Dialog Structure" with sections for "Define Used Business Process Types", "Define Application Object Types" (expanded), and "Define Event Types". The main content area has tabs: General Data, Control Tables, Object Identification (selected), Global Track & Trace Relevance, and Parameter Setup. The "Object Identification" tab contains fields for "Bus. Proc. Type" (ESC_DELIV), "Appl. Obj. Type" (GTT_IDLV_IT) with a description "Extract Inbound Delivery Item information to Global Track and Trace", and "Text" (Inb. Delivery Item). A section titled "Method for determination of AOID" contains a dropdown menu for "AOID Method" set to "Determine from Field", highlighted with a purple border. Another section titled "Application Object ID Source" contains two groups: "First Field to Build Appl. Obj. ID" (Cntrl Tab. Type: 1 Main Object Table, AO ID Field: VBELN) and "Second Field to Build Appl. Obj. ID" (Cntrl Tab. Type: 1 Main Object Table, AO ID Field: POSNR), both highlighted with a purple border. Below these is a section for "Determine AOID By Function" with a field for "AOID Function" containing a small icon.

4.9.7 In the Global Track & Trace Relevance tab, choose the GTT Relevance Method you need.



4.9.8 In the **Parameter Setup** tab, choose the **TrkID Method** as you need.



4.10 Define Event Types for Header Level Extractor

4.10.1 As an example of event's header level tracking introduction, choose the business process type ESC_MATDOC from the **Define Used Business Process Types** on the right side. Double click **Define Event Types**.

Bus. Proc. Type	Update Mode	BPT Process Mode	Description
ESC_MATDOC	Update Task (V1)	Active	Material Document in SAP R/3 Enterprise
ESC_MM_INVOICE	Update Task (V1)	Active	MM Invoice in SAP R/3 Enterprise

4.10.2 Click **New Entries** to create a new event type.

4.10.3 Fill in the **Event Type** and **Text** fields.

4.10.4 Fill in the information required in the **General Data** tab. **HCI for GTT** is the CI Tenant you created in [4.5. Event Function](#) is the extractor function you created in [4.6](#). Check **GTT Relevant**.

Bus. Proc. Type:	ESC_MATDOC
Event Type:	GTT_EVT_IDLV_GR
Text:	Delivery GR

Seq. No.:	10
HCI for GTT:	GTTAPPLOGS

Event Function:	GTT_MIA_IDLV_HD_GR
-----------------	--------------------

<input checked="" type="checkbox"/> GTT Relevant
<input type="checkbox"/> Stop ET Det.
<input type="checkbox"/> Appl. Log Deact

4.10.5 Fill in the Main Object Table and Master Table in the Control Tables tab.

The screenshot shows the SAP Fiori interface for defining event types. The title bar reads "Display View 'Define Event Types': Details". The left sidebar shows "Dialog Structure" with "Define Used Business Process Types" expanded, showing "Define Application Object Types" and "Define Event Types". The main area has tabs "General Data", "Control Tables" (which is selected), and "Global Track & Trace Relevance". Under "Control Tables", there is a section "Data Source for Events" containing fields for "Main Obj. Table" (set to "MATERIAL_HEADER") and "Master Table". Below this is a section "Reference Between Main and Master Table" with fields for "First Field Reference from Main to Master Table" and "Second Field Reference from Main to Master Table".

Caution:

If the event type or application object type is on the header level, then you only need to assign the **Main Object Table**.

If the event type or application object type is on the item level, then you need to assign the **Main Object Table** and **Master Table**, and assign the reference between the **Main Object Table** and **Master Table**.

4.10.6 In the Global Track & Trace Relevance tab, choose the GTT Relevance Method you need.

If you choose the **GTT Relevance Method** as *Check Function*, then you need to define a relevance function according to [4.6](#), and fill in the relevance function name here. Click **Save**.

The screenshot shows the SAP Fiori interface for defining event types. The title bar reads "Display View 'Define Event Types': Details". The left sidebar shows "Dialog Structure" with "Define Used Business Process Types" expanded, showing "Define Application Object Types" and "Define Event Types". The main area has tabs "General Data", "Control Tables" (selected), and "Global Track & Trace Relevance". Under "Global Track & Trace Relevance", there is a field "GTT Rel. Method" with a dropdown menu showing "A Check Function (Function...)" and a field "GTT Rel. Function" containing "GTT_MIA_IDLV_HD_GR". A tooltip "Relevance function for Actu" is shown next to the function name.

4.11 Define Event Types for Item Level Extractor

4.11.1 As an example of the event's item level tracking introduction, choose the business process type ESC_DELIV from the **Define Used Business Process Types** on the right side. Double click **Define Event Types**.

The screenshot shows the SAP Fiori interface with the title "Display View 'Define Used Business Process Types': Overview". On the left, there is a "Dialog Structure" sidebar with sections: "Define Used Business Process Types" (selected), "Define Application Object Types", and "Define Event Types". The main area displays a table titled "Define Used Business Process Types" with columns: Bus. Proc. Type, Update Mode, BPT Process Mode, and Description. Two rows are present: "ESC_DELIV" (selected) with "Update Task (V1)" and "Active" status, and "ESC_FI_CLEARING" with "Update Task (V1)" and "Active" status. A tooltip for "ESC_DELIV" indicates "Delivery in SAP R/3 Enterprise".

4.11.2 Click **New Entries** to create a new event type.

4.11.3 Fill in the **Event Type** and **Text** fields.

4.11.4 Fill in the information required in the **General Data** tab. **HCI for GTT** is the CI Tenant you created in [4.5. Event Function](#) is the extractor function you created in [4.6](#). Check **GTT Relevant**.

The screenshot shows the SAP Fiori interface with the title "Display View 'Define Event Types': Details". On the left, there is a "Dialog Structure" sidebar with sections: "Define Used Business Process Types" (selected), "Define Application Object Types", and "Define Event Types". The main area displays the "General Data" tab. It shows the following fields:

- Bus. Proc. Type: ESC_DELIV
- Event Type: GTT_EVT_IDLV_PA (highlighted with a purple box)
- Text: Put Away Event

Below the General Data tab, there are other tabs: Control Tables and Global Track & Trace Relevance. Further down, there are sections for Sequencing / Destination, Data Setup, and Behavior. In the Behavior section, the checkbox "GTT Relevant" is checked (highlighted with a purple box). Other options like "Stop ET Det." and "Appl. Log Deact" are also listed.

4.11.5 Fill in the Main Object Table and Master Table in the Control Tables tab.

Bus. Proc. Type: ESC_DELIV
Event Type: **GTT_EVT_IDLV_PA** Delivery Item Put Away Event
Text: Put Away Event

Main Obj. Table: **DELIVERY_ITEM_NEW**
Master Table: **DELIVERY_HEADER_NEW**

Old Main Obj. Table: **DELIVERY_ITEM_OLD**
Old Master Table: **DELIVERY_HEADER_OLD**

Uplink Field: **VBELN** Uplink Mode: **R**
Uplink Target Fld: **VBELN** Uplink Const:

Caution:

If the event type or application object type is on the header level, then you only need to assign the **Main Object Table**.

If the event type or application object type is on the item level, then you need to assign the **Main Object Table** and **Master Table**, and assign the reference between the **Main Object Table** and **Master Table**.

4.11.6 In the Global Track & Trace Relevance tab, choose the GTT Relevance Method you need.

If you choose the **GTT Relevance Method** as *Check Function*, then you need to define a relevance function according to [4.6](#), and fill in the relevance function name here. Click **Save**.

Bus. Proc. Type: ESC_DELIV
Event Type: **GTT_EVT_IDLV_PA** Delivery Item Put Away Event
Text: Put Away Event

GTT Rel. Method: **A Check Function (Function)**
GTT Rel. Function: **GTT_MIA_IDLV_IT_PA**

Relevance function for Actu

4.12 Purchase Order Extractor Configuration

4.12.1 Define Application Object Types for Purchase Order Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Appl. Obj. Type	GTT_PO_HD
	Description	Extract purchase order header information to SAP Business Network Global Track and Trace
	Text	Purchase Order Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2012
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ORDER_HEADER_NEW
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_POF_PO_HD_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_POF_PO_HD_TID
	Ctrl Data Function	GTT_POF_PO_HD_OTE
	Planned Event Function	GTT_POF_PO_HD_EE

4.12.2 Define Application Object Types for Purchase Order Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Appl. Obj. Type	GTT_PO_IT
	Description	Extract purchase order item information to SAP Business Network Global Track and Trace
	Text	Purchase Order Item
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2012
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ITEM_NEW
	Master Table	PURCHASE_ORDER_HEADER_NEW
	Del. Obj. Table	PURCHASE_ITEM_OLD
Control Tables – Reference Between Main and Master	Uplink Field	EBELN
	Uplink Mode	R

Table – First Field Reference from Main to Master Table	Uplink Target Fld	EBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_POF_PO_IT_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_POF_PO_IT_TID
	Ctrl Data Function	GTT_POF_PO_IT_OTE
	Planned Event Function	GTT_POF_PO_IT_EE

4.12.3 Define Event Types for Purchase Order Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Event Type	GTT_EVT_PO_IT_CF
	Description	PO Item Confirmation Event
	Text	Confirmation Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_POF_PO_IT_CF
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ITEM_NEW
	Master Table	PURCHASE_ORDER_HEADER_NEW
	Old Main Obj. Table	PURCHASE_ITEM_OLD
	Old Master Table	PURCHASE_ORDER_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	EBELN
	Uplink Mode	R
	Uplink Target Fld	EBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_CF_REL

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Event Type	GTT_EVT_PO_IT_DE
	Description	PO Item Deletion Event

	Text	Deletion Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_POF_PO_IT_DE
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ITEM_NEW
	Master Table	PURCHASE_ORDER_HEADER_NEW
	Old Main Obj. Table	PURCHASE_ITEM_OLD
	Old Master Table	PURCHASE_ORDER_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	EBELN
Global Track & Trace Relevance	Uplink Mode	R
	Uplink Target Fld	EBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_DE_REL

Segment	Field	Value
Header	Bus. Proc. Type	ESC_MATDOC
	Event Type	GTT_EVT_PO_IT_GR
	Description	PO Item Goods Receipt Event
	Text	Goods Receipt Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_POF_PO_IT_GR
	GTT Relevant	X
Control Tables	Main Obj. Table	MATERIAL_SEGMENT
	Master Table	MATERIAL_HEADER
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	MBLNR
	Uplink Mode	R
	Uplink Target Fld	MBLNR
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_GR_REL

4.12.4 Cross-processes for Purchase Order

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
DL_TO_POIT	001	Equal To	Include	GTT_PO_IT
DL_TO_POHD	001	Equal To	Include	GTT_PO_HD

The following entries should be maintained in transaction “ZGTT_EVTYPE_RST - Event Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Event Type
DL_TO_POIT	001	Equal To	Include	GTT_EVT_PO_IT_CF

4.12.5 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the purchase order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_POTYPE_RST - GTT Purchase Doc Type Configuration”, then mark it as active. For example:

Purchasing Document Type	Active
NB	X

4.13 Inbound Delivery Extractor Configuration

4.13.1 Define Application Object Types for Inbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Appl. Obj. Type	GTT_IDLV_HD
	Description	Extract Inbound Delivery Header information to SAP Business Network Global Track and Trace
	Text	Inb. Delivery Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2015
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_MIA_IDLV_HD_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_MIA_IDLV_HD_TID
	Ctrl Data Function	GTT_MIA_IDLV_HD_OTE
	Planned Event Function	GTT_MIA_IDLV_HD_EE

4.13.2 Define Application Object Types for Inbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Appl. Obj. Type	GTT_IDLV_IT
	Description	Extract Inbound Delivery Item information to SAP Business Network Global Track and Trace
	Text	Inb. Delivery Item
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2015
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_ITEM_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_MIA_IDLV_IT_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_MIA_IDLV_IT_TID
	Ctrl Data Function	GTT_MIA_IDLV_IT_OTE
	Planned Event Function	GTT_MIA_IDLV_IT_EE

4.13.3 Define Event Types for Inbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_MATDOC
	Event Type	GTT_EVT_IDLV_GR
	Description	Delivery Header Goods Receipt Event
	Text	Delivery GR
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_IDLV_HD_GR
	GTT Relevant	X
Control Tables	Main Obj. Table	MATERIAL_HEADER
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_HD_GR

4.13.4 Define Event Types for Inbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_IDLV_PA
	Description	Delivery Item Put Away Event
	Text	Put Away Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_IDLV_IT_PA
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_IT_PA

Segment	Field	Value
---------	-------	-------

Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_IDLV_PACK
	Description	Delivery Item Packing Event
	Text	Delivery Packing
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_IDLV_IT_PKNG
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_IT_PKNG

4.13.5 Cross-processes for Inbound Delivery

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
FU_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
FU_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT
SH_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
SH_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT

4.13.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace

Maintain the inbound delivery type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_DLVTYPERST - GTT Delivery Type Configuration”, then mark it as active.

For example:

Delivery Type	Active
---------------	--------

EL	X
----	---

4.14 Sales Order Extractor Configuration

4.14.1 Define Application Object Types for Sales Order Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SORDER
	Appl. Obj. Type	GTT_SO_HD
	Description	Extract sales order header information to SAP Business Network Global Track and Trace
	Text	Sales Order Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	SALES_ORDER_HEADER_NEW
	Del. Obj. Table	SALES_ORDER_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_SO_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_SOF_SO_HD_TID
	Ctrl Data Function	GTT_SOF_SO_HD_OTE
	Planned Event Function	GTT_SOF_SO_HD_EE

4.14.2 Define Application Object Types for Sales Order Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SORDER
	Appl. Obj. Type	GTT_SO_IT
	Description	Extract sales order item information to SAP Business Network Global Track and Trace
	Text	Sales Order Item
General Data	Seq. No.	20
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	SALES_ORDER_ITEMS_NEW

	Master Table	SALES_ORDER_HEADER_NEW
	Del. Obj. Table	SALES_ORDER_ITEMS_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_SO_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_SOF_SO_IT_TID
	Ctrl Data Function	GTT_SOF_SO_IT_OTE
	Planned Event Function	GTT_SOF_SO_IT_EE

4.14.3 Cross-processes for Sales Order

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
DL_TO_SOIT	001	Equal To	Include	GTT_SO_IT
DL_TO_SOHD	001	Equal To	Include	GTT_SO_HD

4.14.4 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the sales order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_SOTYPE_RST - GTT Sales Doc Type Configuration”, then mark it as active.

For example:

Sales Document Type	Active
ZGTT	X

4.15 Outbound Delivery Extractor Configuration

4.15.1 Define Application Object Types for Outbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV

	Appl. Obj. Type	GTT_ODLV_HD
	Description	Extract delivery header information to SAP Business Network Global Track and Trace
	Text	Delivery Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_SOF_ODLV_HD_TID
	Ctrl Data Function	GTT_SOF_ODLV_HD_OTE
	Planned Event Function	GTT_SOF_ODLV_HD_EE

4.15.2 Define Application Object Types for Outbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Appl. Obj. Type	GTT_ODLV_IT
	Description	Extract delivery item information to SAP Business Network Global Track and Trace
	Text	Delivery Item
General Data	Seq. No.	20
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_ITEM_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)

	GTT Rel. Function	GTT_SOF_ODLV_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_SOF_ODLV_IT_TID
	Ctrl Data Function	GTT_SOF_ODLV_IT_OTE
	Planned Event Function	GTT_SOF_ODLV_IT_EE

4.15.3 Define Event Types for Outbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_GI
	Description	Delivery Goods Issue event
	Text	Goods Issue Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_GI
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_GI_REL

4.15.4 Define Event Types for Outbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_PA
	Description	Delivery Item Packing event
	Text	Packing Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_IT_PA
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD

	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_PA_REL

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_PI
	Description	Delivery Item Picking event
	Text	Picking Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_IT_PI
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_PI_REL

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_POD
	Description	Delivery Item POD event
	Text	POD Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_IT_POD
	GTT Relevant	X

Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV POD_REL

4.15.5 Cross-processes for Outbound Delivery

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for Cross-Processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
SH_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLI	001	Equal To	Include	GTT_ODLV_IT

4.15.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace

Maintain the outbound delivery type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_DLVTYPETYPE_RST - GTT Delivery Type Configuration”, then mark it as active.

For example:

Delivery Type	Active
LBNP	X

4.16 Shipment Extractor Configuration

4.16.1 Define Application Object Types for Shipment Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Appl. Obj. Type	GTT_SHP_HD
	Description	Extract Shipment Header information to SAP Business Network Global Track and Trace

	Text	Shipment Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Del. Obj. Table	SHIPMENT_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_MIA_SHP_HD_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_MIA_SHP_HD_TID
	Ctrl Data Function	GTT_MIA_SHP_HD_OTE
	Planned Event Function	GTT_MIA_SHP_HD_EE

4.16.2 Define Event Types for Shipment Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_ARRIVE
	Description	Shipment Header Arrival Event
	Text	Arrival Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_ARR
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_ARR

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_CHECKIN
	Description	Shipment Header Check In Event
	Text	Check In Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_CI
	GTT Relevant	X

Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_CI

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_DEPART
	Description	Shipment Header Departure Event
	Text	Departure Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_DEP
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_DEP

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_LOADEND
	Description	Shipment Header Load End Event
	Text	Load End Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_LE
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_LE

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_LOADSTAR
	Description	Shipment Header Load Start Event

	Text	Load Start Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_LS
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_LS

4.17 Freight Unit Extractor Configuration

4.17.1 Define Application Object Types for Freight Unit Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Appl. Obj. Type	GTT_FU
	Description	Extract FU Information to SAP Business Network Global Track and Trace
	Text	FU Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
	Del. Obj. Table	TOR_ROOT
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID By Function	AOID Function	GTT_STS_AOID_TOR
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_FU_HD_REL
Parameter Setup	Trk.ID Method	Determine by Function
	Tr. Function	GTT_TS_FU_HD_TID
	Ctrl Data Function	GTT_TS_FU_HD_OTE
	Planned Event Function	GTT_TS_FU_HD_EE

4.17.2 Define Event Types for Freight Unit Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR

	Event Type	GTT_EVT_TOR_ARRIVE
	Description	FO/FB/FU Arrival Event
	Text	Arrival Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_ARRIVAL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_ARRIVE

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_COUPLE
	Description	FO/FB/FU Coupling Event
	Text	Coupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_COUPLING
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_COUP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DECOPPLE
	Description	FO/FB/FU Decoupling Event
	Text	Decoupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DECOUPL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DECP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLSTART
	Description	FO/FB/FU Unloading Start Event
	Text	Unloading Start
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_STR
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_USTR

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DELAY
	Description	FO/FB/FU Delay Event
	Text	Delay Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DELAY
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DELAY

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DEPART
	Description	FO/FB/FU Departure Event
	Text	Departure Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DEPART
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)

	GTT Rel. Function	GTT_TS_TOR_DEPART
--	-------------------	-------------------

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_FU_DELAY
	Description	FU Delay Event
	Text	FU Delay Event
General Data	Seq. No.	0
	HCI for GTT	GTAPPLOGS
	Event Function	GTT_TS_TOR_FU_DELAY
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_FU_DELAY

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADEND
	Description	FO/FB/FU Loading End Event
	Text	Loading End Event
General Data	Seq. No.	0
	HCI for GTT	GTAPPLOGS
	Event Function	GTT_TS_TOR_LOAD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LEND

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADSTRT
	Description	FO/FB/FU Loading Start Event
	Text	Loading Start Event
General Data	Seq. No.	0
	HCI for GTT	GTAPPLOGS
	Event Function	GTT_TS_TOR_LOAD_STR
	GTT Relevant	X

Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LSTR

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POD
	Description	FO/FB/FU Proof of Delivery Event
	Text	POD Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POD
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POD

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POPU
	Description	FO/FB/FU Proof of Pickup Event
	Text	POPU Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POPU
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POPU

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLEND
	Description	FO/FB/FU Unloading End Event
	Text	Unloading End Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_UEND

4.18 Road Freight Order/Ocean Booking/Air Booking Extractor Configuration

4.18.1 Define Application Object Types for Road Freight Order/Ocean booking/Air Booking Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Appl. Obj. Type	GTT_SHP_HD
	Description	Extract FO/FB information to SAP Business Network Global Track and Trace
	Text	FO/FB Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
	Del. Obj. Table	TOR_ROOT
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID By Function	AOID Function	GTT_STS_AOID_TOR
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_FO_HD_REL
Parameter Setup	Trk.ID Method	Determine by Function
	Tr. Function	GTT_TS_FO_HD_TID
	Ctrl Data Function	GTT_TS_FO_HD_OTE
	Planned Event Function	GTT_TS_FO_HD_EE

4.18.2 Define Event Types for Road Freight Order/Ocean Booking/Air Booking Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_ARRIVE
	Description	FO/FB/FU Arrival Event
	Text	Arrival Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_ARRIVAL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT

Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_ARRIVE

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_COUPLE
	Description	FO/FB/FU Coupling Event
	Text	Coupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_COUPLING
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_COUP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DECOUPLE
	Description	FO/FB/FU Decoupling Event
	Text	Decoupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DECOUPL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DECP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLSTART
	Description	FO/FB/FU Unloading Start Event
	Text	Unloading Start
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_STR
	GTT Relevant	X

Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_USTR

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DELAY
	Description	FO/FB/FU Delay Event
	Text	Delay Event
General Data	Seq. No.	0
	HCI for GTT	GTAPPLOGS
	Event Function	GTT_TS_TOR_DELAY
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DELAY

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DEPART
	Description	FO/FB/FU Departure Event
	Text	Departure Event
General Data	Seq. No.	0
	HCI for GTT	GTAPPLOGS
	Event Function	GTT_TS_TOR_DEPART
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DEPART

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADEND
	Description	FO/FB/FU Loading End Event
	Text	Loading End Event
General Data	Seq. No.	0
	HCI for GTT	GTAPPLOGS

	Event Function	GTT_TS_TOR_LOAD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LEND

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADSTRT
	Description	FO/FB/FU Loading Start Event
	Text	Loading Start Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_LOAD_STR
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LSTR

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POD
	Description	FO/FB/FU Proof of Delivery Event
	Text	POD Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POD
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POD

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POPU
	Description	FO/FB/FU Proof of Pickup Event
	Text	POPU Event

General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POPU
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POPU

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLEND
	Description	FO/FB/FU Unloading End Event
	Text	Unloading End Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_UEND

5. CONFIGURATION AND CODING GUIDE – ADVANCED

This chapter has been moved to the guide *How to Send Documents from SAP S/4HANA to SAP Business Network Global Track and Trace* on SAP Help Portal. Please check the Coding Tips section of this guide. You can find this guide at <http://help.sap.com/gtt>.

6 KNOWN ISSUES

6.1 Planned Event Extension Not Enabled

Currently, on SAP S/4HANA side, the EXTENSION segment of process IDOC is not enabled for the planned event part, which means that you cannot make the user-defined fields for planned events in the *Manage Models* app.

The workaround is to make use of Control Parameter's segment in IDOC and make the field mapping on the tracked process level in the *Manage Models* app.

6.2 One-time locations Relevant

- When the supplier address is changed in the purchase order header, the purchase order item IDOC cannot be triggered. So, the change cannot be updated to its purchase order items in the GTT system.
- After the sales order and the outbound delivery are created, then if you change the address in the sales order, the change cannot be updated to the outbound delivery in the GTT system, because no new outbound delivery IDOC is generated and sent to the GTT system. The same goes for the purchase order and the inbound delivery.
- After the outbound delivery and the LE-TRA shipment are created, then if you change the address in the outbound delivery, the change cannot be updated to the LE-TRA shipment in the GTT system, because no new LE-TRA shipment IDOC is generated and sent to the GTT system. The same goes for the inbound delivery and the LE-TRA shipment.
- If you change the address in the LE-TRA shipment, the change can be updated to the outbound/inbound delivery header through cross-process updates. But it cannot be updated to the item level.

APPENDIX ONE: DEFINE THE UNPLANNED EVENTS FOR AIR BOOKING

You need to define the following unplanned events for air booking before they can be synchronized back from GTT to TM:

- Flight Booked
- Manifest Ready
- Received from Shipper
- Consignee Notified.

To define these unplanned events, do the following:

Note: here the unplanned event "Flight Booked" is used as an example.

1. On the **Display IMG** page, click **Transportation Management-> Integration-> Tracking and Tracing of Processes and Documents-> Define Transportation Activities for Tracking and Tracing**.

2. Select **Event for Business Document** and click **New Entries**.

Event	Description	Transp Act	Stop Cat
ARRIVAL_DOOR	Arrival at Door	11	
ARRIV_DEST	Arrival at Destination	04	I S
BLOCK_FOR_EXEC	Block for Execution	99	


3. Input the **Event name, Description, Transp Act** and Click **Save**.

Event	Description	Transp Act	Stop Cat	Internal
FLIGHT_BOOKED	Flight Booked	99		


4. Select the event "FLIGHT_BOOKED", then double click **Assignment of Events to Business Object**.

Event	Description	Transp Act	Stop Cat
FLIGHT_BOOKED	Flight Booked	99	
GEN_DISCRP	General Discrepancy	99	

5. Click **New Entries**.



6. Select "BO Freight Booking" and Click **Save**.



Results:

The configuration results for these event types should be as follows:

Event	Description	Transportation Activity	Stop Category	Event relevance for category
FLIGHT_BOOKED	Flight Booked	99	blank	BO (Freight Booking)
MANIFEST_READY	Manifest Ready	99	blank	BO (Freight Booking)
RCVD_FROM_SHIPPER	Received from Shipper	99	blank	BO (Freight Booking)
CONSIGNEE_NOTIFIED	Consignee Notified	99	blank	BO (Freight Booking)

Now you can go on to configure for synchronizing these unplanned events back to TM. For configuration details, see [Synchronize Actual Events Back to TM System](#). If the events still cannot be synchronized back to TM, please check the SAP Note [3010748 - Allow unexpected events without location reference in TransportationEventBulkNotification](#).

APPENDIX TWO: FAQS

This chapter provides you with answers to questions commonly asked about the configuration.

Q1: After the configuration of GTT and SAP TM systems, we found that the freight unit / freight order / freight booking IDOC cannot be sent to SAP Business Network Global Track and Trace, how can we do the troubleshooting?

Step 1: Check the integration of SAP TM and SAP EM

The Post Processing Framework (PPF) is used to trigger the communication from SAP Transportation Management (SAP TM) to SAP Event Management (SAP EM). You need to maintain the output management adapter for this communication to work.

- a. Log onto SAP Business Client, enter T-code SPRO and then click **SAP Reference IMG** to open the **Display IMG** page. Go to node **Cross-Application Components -> Processes and Tools for Enterprise Applications -> Reusable Objects and Functions for BOPF Environment -> PPF Adapter for Output Management -> Maintain Output Management Adapter Settings**.
- b. In the **Dialog Structure** section, choose **Direct Output Agents (w/o PPF & w/o History)**.
- c. Choose the entry shown in the screenshot and enable it.

The screenshot shows the SAP Reference IMG interface with the title "Display View 'Direct Output Agents (w/o PPF & w/o History)': Overview". The left sidebar shows the "Dialog Structure" tree with nodes like "PPF Output Agents for BO Nodes", "Assign PPF Profiles", "Action Settings", and "Direct Output Agents (w/o PPF & w/o History)". The main area displays a table titled "Direct Output Agents (w/o PPF & w/o History)" with columns: Business Object, Node, Agent Name, Description, Enable, and Ch. One row is selected: "/SCMTMS/TOR" with Node "ROOT" and Agent Name "SEND_EM_DATA_FROM_TOR". The "Enable" checkbox is checked. Other rows include "/SCMTMS/TOR" (Node ROOT, Agent TOR_BW_EXTRACTION), "/SCMTMS/trigger_collector" (Node ROOT, Agent TRIGGER_COLLECTOR), "/SCMTMS/TRQ" (Node ROOT, Agent DPP_SORT_DETERMINATION), "/SCMTMS/TRQ" (Node ROOT, Agent SEND_EM_DATA_FROM_TRQ), "/SCMTMS/TRQ" (Node ROOT, Agent TRQ_BW_EXTRACTION), and "/SCMTMS/WAYBILLNO" (Node ROOT, Agent DPP_SORT_DETERMINATION).

The screenshot shows the SAP Reference IMG interface with the title "Display View 'Direct Output Agents (w/o PPF & w/o History)': Details". The left sidebar shows the "Dialog Structure" tree with the "Direct Output Agents (w/o PPF & w/o History)" node selected. The main area displays a form for configuring the selected agent. The "Business Object" field is set to "/SCMTMS/TOR", the "Node" field is set to "ROOT", and the "Agent Name" field is set to "SEND_EM_DATA_FROM_TOR". The "Description" field contains the note "Call SAP EM (recommended, check note 1842397 for details)". The "Enable" checkbox is checked. Other configuration fields include "Incl. Child Chgs", "Synch/Asynch" (set to "B Has Uncritical o/p: Process after Commit (background)", dropdown menu), "Processor Class" (set to "/SCMTMS/CL_OUTMGMT_EXEC_TOR"), and three "User-Def. Func." fields (empty).

- d. In the **Dialog Structure** section, choose **Nodes for Before Image**.
e. Create the following three entries:

Business Object	Node	Sub Node Name
/SCMTMS/TOR	ROOT	EXECUTIONINFORMATION
/SCMTMS/TOR	ROOT	ITEM_TR
/SCMTMS/TOR	ROOT	STOP

Step 2: Check the trigger point of the generation of freight unit / freight order / freight booking IDOC

- a. Go to T-code SE19, fill in the **Enhancement Implementation** with "ZGTT_STS_EI_SEND_TOR_DATA" and click **Display**.

Enhancement Implementation: `ZGTT_STS_EI_SEND_TOR_DATA`

Display Change

- b. Ensure that the **Enhancement Implementation** “ZGTT_STS_EI_SEND_TOR_DATA” is active. In the **Enh. Implementation Elements** tab, ensure that **BAdl Implementation** “ZGTT_STS_BI_SEND_TOR_DATA” is active.

Enhancement Implementation ZGTT_STS_EI_SEND_TOR_DATA Display

Properties History Technical Details Enh. Implementation Elements

Enhancement Implementation: ZGTT_STS_EI_SEND_TOR_DATA Active

BAdl Implementation: ZGTT_STS_BI_SEND_TOR_DATA Description: Send TOR Data

Runtime Behavior: Implementation is active Runtime Behavior: The implementation will be called

Properties of BAdl Definition

BAdl Definition Name: /SCMTMS/SEND_TOR_DATA Description: Send TOR Data to Event Management Interface: /SCMTMS/IF_SEND_TOR_DATA Instance Creation Mode: No Reuse of BAdl Instance

Step 3: Check the freight unit type settings

- On the IMG, go to **SAP Transportation Management -> Transportation Management -> Planning -> Freight Unit -> Define Freight Unit Types**.
- In the table, open the applicable freight unit type to be tracked with SAP Event Management.
 - In the **Integration Settings**, fill in the **Application Obj.Type** field as follows:

Dangerous Goods Profile: []

Customs Profile: []

Application Obj.Type: **GTT_FU**

BW Relevance

Note: make sure the value you filled in is the same as the ones in the other two fields:

- Appl.Obj.Type** field
(Navigation Path: **IMG->Integration with Other SAP Components-> Interface to Global Track and Trace -> Define Application Interface**, choose **Define Used Business Process Types, Appl. Object Types and Event Types**. In the table, choose **Business Process Type TMS_TOR** and click **Define Application Object Types**.)

SAP

Display View "Define Application Object Types": Details

Dialog Structure

- Define Used Business Process Types
 - Define Application Object Types
 - Define Event Types

Bus. Proc. Type: TMS_TOR
Appl. Obj. Type: GTT_FU Extract FU Information to Global Track and Trace
Text: FU Header

General Data Control Tables Object Identification Global Track & Trace Relevance Parameter Setup

Sequencing / Destination

Seq. No.: 10
CI for GTT: GTTAPPLOGS CI Tenant for GTT Standard APP

Business Object Reference

Object Type:
BO Setup Fnct:

○ Application Object Type field in the “gttft1” model in the Manage Models app.

SAP Model Details Internal - Test

gttft1 Active

GTT standard model

Namespace: com.lbngttapps.gtt.app.gttft1 Correlation Level: 5 Model Category: Standard

Tracked Process Field Type Pool Event Type Pool Code List IDOC Integration Visibility Provider Integration Planned Event Extension Event to Action

Tracked Process: FreightUnit Integration Switch:

Tracked Process Mapping

ERP Object Type: Others Application Object Type: GTT_FU

- In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

Execution Settings

Execution Tracking Relevance: 3 Execution Tracking with External Ev...

Display Mode for Execution Tab: Actual Events from TM and EM, Expe...

Propagation Mode: Standard Propagation

Last Exp. Event: UNLOAD_END

Immediate Processing

Step 4: Check the freight order type settings

- a. On the IMG, go to **SAP Transportation Management > Transportation Management > Freight Order Management > Freight Order > Define Freight Order Types**.
- b. In the table, open the applicable freight order type to be tracked with SAP Event Management.
 - In the **Integration Settings**, fill in the **Application Object Type** field as follows:

Integration Settings

Dangerous Goods Profile:	<input type="text" value="DG1"/>
Customs Profile:	<input type="text"/>
Document Creation Relevance:	<input type="text" value="N No External Document Creation"/> <input type="button" value="▼"/>
Delivery Profile:	<input type="text"/>
EWM Integration Profile:	<input type="text"/>
Application Object Type:	<input style="border: 2px solid #800080; background-color: #f0f0ff;" type="text" value="GTT_SHP_HD"/>
<input checked="" type="checkbox"/> BW Relevance	

Note: make sure the value you filled in is the same as the ones in the other two fields:

- **Appl. Obj. Type** field
(Navigation Path: **IMG-> Integration with Other SAP Components-> Interface to Global Track and Trace -> Define Application Interface**, choose **Define Used Business Process Types, Appl. Object Types and Event Types**, choose **Business Process Type TMS_TOR->Define Application Object Types.**)
- **Application Object Type** field in the “gttft1” model in the Manage Models app.

- In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

Execution Settings

The screenshot shows the SAP Execution Settings dialog. The 'Execution Tracking Relevance' dropdown is highlighted with a purple border and contains the value '3 Execution Tracking with External Event M...'. Other fields include 'Check Condition "Ready for Exec":' (empty), 'Display Mode for Execution Tab:' (set to 'Actual Events from TM and EM, Expected ...'), 'Expected Event for Goods Issue:' (empty), 'Expected Event for Goods Receipt:' (empty), and 'Last Exp. Event:' (set to 'ARRIV_DEST'). A checkbox for 'Immediate Processing' is unchecked. Below it, 'Execution Propagation Mode:' is set to 'Standard Propagation' and 'Discrepancy Profile:' is empty.

Step 5: Check the freight booking type settings

- a. On the IMG, go to **SAP Transportation Management > Transportation Management > Freight Order Management > Freight Booking > Define Freight Booking Types**.
- b. In the table, open the applicable freight booking type to be tracked with SAP Event Management.

- In the **Integration Settings**, fill in the **Application Object Type** field as follows:

The screenshot shows the SAP Integration Settings dialog. The 'Application Object Type' dropdown is highlighted with a purple border and contains the value 'GTT_SHP_HD'. Other fields include 'Dangerous Goods Profile:' (set to 'DG1'), 'Customs Profile:' (empty), 'Document Creation Relevance:' (empty), 'Delivery Profile:' (empty), and 'EWM Integr. Profile:' (empty). A checkbox for 'BW Relevance' is unchecked.

Note: make sure the value you filled in is the same as the ones in the other two fields:

- **Appl. Obj. Type** field
(Navigation Path: **IMG->Integration with Other SAP Components-> Interface to Global Track and Trace -> Define Application Interface**, choose **Define Used Business Process Types, Appl. Object Types and Event Types**, choose **Business Process Type TMS_TOR->Define Application Object Types**.)
- **Application Object Type** field in the “gttft1” model in the Manage Models app.

- In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

Execution Settings

Execution Tracking Relevance:	3 Execution Tracking with External Event Management
Display Mode for Execution Tab:	Actual Events from TM and EM, Expected Events from EM
Immediate Processing:	Life Cycle Is Not to Be Set to "In Process" Immediately
Expected Event for Goods Issue:	
Expected Event for Goods Receipt:	
Last Exp. Event:	UNLOAD_END
Execution Propagation Mode:	Standard Propagation
Check Condition "Ready for Exec":	
Discrepancy Profile:	


Step 6: Check the freight order / freight booking master data

To send freight orders or freight bookings to SAP Business Network Global Track and Trace, do the following:


- Assign the carrier.
- Change the execution status.
 - For freight orders: in the **Execution Status** tab on the top, change the **Execution Status** to “Set to Ready for Transportation Execution” or “Set to In Execution”.

The screenshot shows the SAP Fiori interface for editing a freight order. The top navigation bar includes 'Edit GTT Standard Freight Order Type AccAWS 6100063618'. The main area has tabs for General Data, Business Partner, Items, Overview, Stages, Utilization, Subcontracting, Schedule, Set Status, and Display Settings. The General Data tab is active. It contains sections for Truck (Means of Transport, Vehicle, Registration Country/Region No., Total/Capacity), Cargo Information (Cargo Weight, Volume, Quantity, Total Weight), and General Information (Document Type, Description, Origin of Freight Order). A context menu is open at the top right, listing options such as Load Plan Status (Stop), Execution Status (highlighted), Fixing, Customs, Charges/Settlement, Cancel Document, Load Plan Status (Packaging), and Load Plan Status (Load Planning). Callout 1 points to the 'Carrier' field, which is set to 'LBN_CAR100'. Callout 2 points to the 'Set to In Execution' option in the context menu.

- For freight bookings:
 - Air booking: in the **Execution Status** tab on the top, change the **Execution Status** to "Set to MAWB Finalized" or "Set to In Execution".



- Ocean booking: in the **Execution Status** tab on the top, change the **Execution Status** to "Set to Ready for Transportation Execution" or "Set to In Execution".



Debugging

If the issue still exists, you can perform the following steps to debug in the extractor code:

- On the IMG, go to node **Cross-Application Components -> Processes and Tools for Enterprise Applications ->Reusable Objects and Functions for BOPF Environment -> PPF Adapter for Output Management -> Maintain Output Management Adapter Settings.**
- In the **Dialog Structure** section, choose **Direct Output Agents (w/o PPF & w/o History)**. Ensure that the following entry is enabled:

Business Object	Node	Agent Name	Description	Enable	Ch
/SCMTMS/TOR	ROOT	SEND_EM_DATA_FROM_TOR	Call SAP EM (recommended, check note 1842397 for details)	<input checked="" type="checkbox"/>	
/SCMTMS/TOR	ROOT	SEND_EM_DATA_FROM_TOR_ASYNC	Call SAP EM (not recommended, check note 1842397 for detail)	<input type="checkbox"/>	
/SCMTMS/TOR	ROOT	TOR_BW_EXTRACTION	TOR Delta Extraction to SAP BW	<input type="checkbox"/>	
/SCMTMS/TRIGGER_COLLECTOR	ROOT	TRIGGER_COLLECTOR	Collects triggers and executes bgRFC units to process them	<input checked="" type="checkbox"/>	
/SCMTMS/TRQ	ROOT	DPP_SORT_DETERMINATION	DPP: DOA Agent to determine/write SoRT Information for TRQ	<input type="checkbox"/>	
/SCMTMS/TRQ	ROOT	SEND_EM_DATA_FROM_TRQ	Send EM Data from Transportation Request (BO TRQ)	<input type="checkbox"/>	
/SCMTMS/TRQ	ROOT	TRQ_BW_EXTRACTION	TRQ Delta Extraction to SAP BW	<input type="checkbox"/>	
/SCMTMS/WAYBILLNO	ROOT	DPP_SORT_DETERMINATION	DPP: DOA Agent to determine/write SoRT Information for WBN	<input type="checkbox"/>	

Note: in this entry, the value of **Synch/Asynch** column is "Has Critical o/p: Process during Save - before Commit".

- Set a break point in method /SCMTMS/IF_SEND_TOR_DATA~CALL_EVENT_MGR of the BAdI implementing class ZCL_GTT_STS_SEND_TOR_DATA.
- For the scenario when the freight unit watches the freight order, set additional break point in below places:
 - In method ZIF_GTT_STS_BO_READER~CHECK_RELEVANCE of class ZCL_GTT_STS_BO_FU_READER, check the value of "rv_result". If it is "T", it means

- the freight unit IDOC can be generated. Otherwise, the freight unit IDOC cannot be generated.
- In method ZIF_GTT_STS_BO_READER~CHECK_RELEVANCE of class ZCL_GTT_STS_BO_FO_READER, check the value of "rv_result". If it is "T", it means the freight order IDOC can be generated. Otherwise, the freight order IDOC cannot be generated.

Q2: How to add customized planned event and synchronize this event back to SAP TM?

Suppose you want to add the planned event type "quality inspection" for the freight order tracked process, do the following:

Step 1: Create a planned event type in the GTT standard model "gttft1" in the Manage Models app

- Launch the Manage Models app and go to the GTT standard model "gttft1".
- In the **Event Type Pool** tab, click **Create** and fill in the event information in the dialogue. For details, see "[Create Event Type](#)" section in [Guide for Model Administrators](#).
Note: the event type must start with "ZZ". For example ZZINSPECTION.
- Assign the newly created event type to the shipment tracked process.
 - In the **Tracked Process** tab, choose **Admissible Planned Events** from the dropdown list on the right and click **Add**.
 - In the **Details** tab of the dialogue, choose the **Event Type** that you created from the dropdown list and fill in the rest of information.
- Configure the IDOC mapping
 - Click **Edit** on the top. In the **IDOC Integration** tab, for **Tracked Process** field, choose "Shipment" from the dropdown list.
 - Under **Tracked Process / Events**, fill in **IDOC** and **Event Code** for the newly created event type.

The screenshot shows the SAP Manage Models app interface. The top navigation bar includes tabs for Tracked Process, Field Type Pool, Event Type Pool, Code List, **IDOC Integration** (which is currently selected), and Visibility Provider Integration. Below the tabs, there's a dropdown labeled "Tracked Process:" set to "Shipment". A sub-section titled "Tracked Process Mapping" shows the "ERP Object Type" as "Others". The main area displays a table titled "Tracked Process / Events (54)". The table has columns for Name, IDOC, and Event Code. One row is highlighted with a purple border, showing "ZZINSPECTION" in the Name column, "E1EVMDR02" in the IDOC column, and "ZZ_INSPECTION" in the Event Code column. To the right of the table, there are two vertical panes: "User M" and "Field".

Tracked Process / Events (54)		
Name	IDOC	Event Code
GateInEmpty	E1EVMDR02	GATEIN_EMPTY
GateInFull	E1EVMDR02	GATEIN_FULL
GateOutEmpty	E1EVMDR02	GATEOUT_EMPTY
GateOutFull	E1EVMDR02	GATEOUT_FULL
ZZINSPECTION	E1EVMDR02	ZZ_INSPECTION

- In the **User Script Before Standard Script** section, add your script for synchronizing back the customized event to SAP TM.

Example:

```
var inspection_event = modelNamespace + ".Shipment.ZZINSPECTION";
if (inspection_event == actualEvent.eventType) {
```

```

        eventForwardToTM = true;
    }
}

```

- f. Save your changes and click **Deploy** on the top right to deploy the model. Once the model is successfully deployed, you can see **Active** on the model card with its last operation status "Deployment Success".

Step 2: Add the ABAP Implementation Code

- a. Navigate to the method ZIF_GTT_STS_PE_FILLER~GET_PLANNED_EVENTS of class ZCL_GTT_STS_PE_FO_FILLER in the system.
- b. Add the planned event type that you created in the Manage Models app as milestone event. For coding tips, see chapter [5](#) in this guide.

Note: when you add the planned event type, remember that the event name here must be the same as the event code that you previously maintained in the IDOC mapping.

Step 3: Add the above customized event In SAP TM.

- a. On the **Display IMG** page, click **Transportation Management-> Integration-> Tracking and Tracing of Processes and Documents-> Define Transportation Activities for Tracking and Tracing**.
- b. Select **Event for Business Document** and click **New Entries**.

Event	Description	Transp Act	Sto
ARRIVAL_DOOR	Arrival at Door	11	
ARRIV_DEST	Arrival at Destination	04	I S
BLOCK_FOR_EXEC	Block for Execution	99	

c. Input the **Event name**, **Description**, **Transp Act** and Click **Save**.

Event	Description	Transp Act	Stop Cat	Internal
ZZ_INSPECTION	Quality inspection	99		<input checked="" type="checkbox"/>

d. Select the event "ZZ_INSPECTION", then double click **Assignment of Events to Business Object**.

e. Click **New Entries**.

f. Select "TO Freight Order" and Click **Save**.

Now you can go on to configure for synchronizing events back to TM. For configuration details, see [Synchronize Actual Events Back to TM System](#). If the events still cannot be synchronized back to TM, please check the SAP Note [3010748 - Allow unexpected events without location reference in TransportationEventBulkNotification](#).

Q3: How to update business partner's LBN ID?

To update the LBN ID in SAP Transportation Management (SAP TM) for a logistics service provider (your business partner), proceed as follows in SAP TM:

Step 1: Define Identification Categories for LBN Identification Number

Go to SAP Customizing Implementation Guide under **Cross-Application Components->SAP Business Partner->Business Partner->Basic Settings->Identification Numbers->Define Identification Categories** and maintain the following entry:

ID Cat.	Description	ID Unique	Disp. Only	One ID->BP	Identification Schema
LBN001	LBN Identification			X	

Step 2: Define Identification Types for LBN Identification Number

Go to SAP Customizing Implementation Guide under **Cross-Application Components->SAP Business Partner->Business Partner->Basic Settings->Identification Numbers->Define Identification Types**. Create a new ID Type as follows:

ID Type	Description	ID Categ.	Persons	Organizations
LBN001	LBN Identification	LBN001	X	X


Step 3: Update Business Partner's LBN ID

- Go to the **Manage Business Partner** transaction (transaction BP).
- Set the filtering criteria to find the business partner for which you want to update the LBN ID. Double-click the business partner to open its **Display Organization** page.
- Go to the **Identification** tab. In the **Identification Numbers** section, enter “LBN001” in the **IDType** column.
- In the **Identification Number** field, enter the LBN ID and save your changes.

Q4: How is the connection established between SAP S/4HANA and SAP Business Network Global Track and Trace? Do I need to configure PI in SAP S/4HANA?

When saving the transaction data, the asynchronous IDOC was sent to establish the connection between SAP S/4HANA and SAP Business Network Global Track and Trace. You don't need to set up PI in SAP S/4HANA.

The data process flow is as below:



Q5: What scenarios are supported in SAP Business Network Global Track and Trace?

1) Purchase Order -> Inbound Delivery -> Shipment.



2) Purchase Order -> Inbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.



3) Sales Order -> Outbound Delivery -> Shipment.




4) Sales Order -> Outbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.



5) Stock Transport Order


Scenario A:

Purchase Order -> Outbound Delivery -> Shipment.



Scenario B:

Purchase Order -> Outbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.



Q6: Do sample codes support one-time locations? Where can I maintain the one-time location address?

Yes. You can maintain one-time locations in the following fields:

Tracked Processes	Fields
Purchase Order	Address in Purchase Order header
Purchase Order Item	Delivery Address in Purchase Order Item
Inbound Delivery	Goto->Header->Partners->Partner Function "Supplier"
Shipment	Fields under Stages->Departure point / Destination or you can directly add the one-time location address in the stage
Sales Order	Fields under Goto->Header->Partner->Partner Function "Sold-To Party" or "Ship-To Party"
Outbound Delivery	Fields under Goto->Header->Partners->Partner Function "Ship-To Party"

Q7: How to stop sending unnecessary IDOCs from SAP S/4HANA to the GTT system?

To do so, you should not mark application object types/event types as “GTT Relevant”.

Take the purchase order as an example, you can perform the following steps:

- In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface**.
- Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types**.
- Choose the business process type “ESC_PURORD” and double click **Define Application Object Types** on the left.
- Uncheck the “GTT Relevant” box for application object types “GTT_PO_HD” and “GTT_PO_IT”, and it will stop sending control parameter / planned events / tracking ID of the purchase order and its items.

Application ObjType	Seq. No.	Description	CI for GTT	Object Type	GTT Relev.
GTT_PO_HD	10	Purchase Order Head for Procurement Visibility (GTT)	GTTAPPLOGS	BUS2012	<input type="checkbox"/>
GTT_PO_IT	10	Purchase Order Item for Procurement Visibility (GTT)	GTTAPPLOGS	BUS2012	<input type="checkbox"/>
PCM10_ITEM		Purchase Order Item for Procurement Visibility		BUS2012	<input type="checkbox"/>

- Uncheck the “GTT Relevant” box for event types “GTT_EVT_PO_IT_CF” and “GTT_EVT_PO_IT_DE”, and it will stop sending actual events of the purchase order and its items.

Business Process Type	Event Type	Description	Text	GTT Relevant
ESC_PURORD	GTT_EVT_PO_IT_CF	PO Item Confirmation Event	Confirmation Event	<input type="checkbox"/>
ESC_PURORD	GTT_EVT_PO_IT_DE	PO Item Deletion Event	Deletion Event	<input type="checkbox"/>
ESC_PURORD	PCM10_ACKNOWL	Acknowledgement for Procurement Visibility	Acknowl. Proc. Visib.	<input type="checkbox"/>
ESC_PURORD	PCM10_PO_CHANGE	Purchase Order Changes for Procurement Visibility	PO Chg. Proc. Visib.	<input type="checkbox"/>

Q8: How to deactivate or activate the application log?

Take the purchase order as an example, to deactivate the application log for application object types and event types, do the following:

- In Display IMG page, click **Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface**.
- Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types**.
- Choose the business process type “ESC_PURORD”
- To deactivate the application log for application object types, double click **Define Application Object Types** on the left, then check the “Application Log Deactivation” box for application object types “GTT_PO_HD” and “GTT_PO_IT”. It will stop recording the application log for control parameter / planned events / tracking ID of the purchase order and its items.

Application ObjType	Seq. No.	Description	CI for GTT	Object Type	GTT Relev.	Log. Deac.	BO Setup Functor
GTT_PO_HD	10	Purchase Order Head for Procurement Visibility (GTT)	GTTAPPLOGS	BUS2012	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	PCM10_ITEM
GTT_PO_IT	10	Purchase Order Item for Procurement Visibility (GTT)	GTTAPPLOGS	BUS2012	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	
PCM10_ITEM	0	Purchase Order Item for Procurement Visibility		BUS2012	<input type="checkbox"/>	<input type="checkbox"/>	

- e. To deactivate the application log for event types, double click **Define Event Types** on the left, then check the “Application Log Deactivation” box for event types “GTT_EVT_PO_IT_CF” and “GTT_EVT_PO_IT_DE”. It will stop recording the application log for actual events of the purchase order and its items.

Business Process Type	Event Type	Description	Text	GTTR	Log. Deac.	Seq. No.
ESC_PURORD	GTT_EVT_PO_IT_CF	PO Item Confirmation Event	Confirmation Event	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	10
ESC_PURORD	GTT_EVT_PO_IT_DE	PO Item Deletion Event	Deletion Event	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	10
ESC_PURORD	PCM10_ACKNOWL	Acknowledgement for Procurement Visibility	Acknwl. Proc. Visib.	<input type="checkbox"/>	<input type="checkbox"/>	0
ESC_PURORD	PCM10_PO_CHANGE	Purchase Order Changes for Procurement Visibility	PO Chg. Proc. Visib.	<input type="checkbox"/>	<input type="checkbox"/>	0

To activate the application log for application object types and event types, you can uncheck the “Application Log Deactivation” box.

www.sap.com/contactsap

© 2022 SAP SE or an SAP affiliate company. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company.

The information contained herein may be changed without prior notice. Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

In particular, SAP SE or its affiliated companies have no obligation to pursue any course of business outlined in this document or any related presentation, or to develop or release any functionality mentioned therein. This document, or any related presentation, and SAP SE's or its affiliated companies' strategy and possible future developments, products, and/or platform directions and functionality are all subject to change and may be changed by SAP SE or its affiliated companies at any time for any reason without notice. The information in this document is not a commitment, promise, or legal obligation to deliver any material, code, or functionality. All forward-looking statements are subject to various risks and uncertainties that could cause actual results to differ materially from expectations. Readers are cautioned not to place undue reliance on these forward-looking statements, and they should not be relied upon in making purchasing decisions.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies. See www.sap.com/trademark for additional trademark information and notices.