

Administration Guide

SQream Technologies

Version 2019.2



Copyright © 2010-2019. All rights reserved.

This document is provided for information purposes only and the contents hereof are subject to change without notice. This document is not warranted to be error-free, nor subject to any other warranties or conditions, whether expressed orally or implied in law, including implied warranties and conditions of merchant- ability or fitness for a particular purpose.

We specifically disclaim any liability with respect to this document and no contractual obligations are formed either directly or indirectly by this document.

This document may not be reproduced in any form, for any purpose, without our prior written permission.



Table of Contents

| Table of Contents | 3 |
|--|----|
| SQream DB Administrator Guide | 5 |
| Overview | 5 |
| Administration Guide | 6 |
| Getting Started | 7 |
| Understanding the SQream DB environment | 7 |
| Setting up SQream DB | 8 |
| Create the cluster | 9 |
| Configure the instances | 9 |
| Configuring instances parameters | 10 |
| Starting and Stopping the SQream DB daemons | 11 |
| SQream based on Docker | 12 |
| SQream based on RPM | 12 |
| Connect to the SQream DB server with ClientCmd | 14 |
| Using SSL Server Authentication with SQream | 14 |
| Enabling SSL server authentication within SQream Instance: | 14 |
| Configure SSL Authentication for JDBC/ODBC drivers | 15 |
| Adding SSL to JDBC | 15 |
| Adding SSL to ODBC | 15 |
| Highly available installations | 15 |
| Operations | 16 |
| Upgrading a version | 16 |
| Key administration concepts | 16 |
| Monitoring the system | 16 |
| From the OS | 16 |
| From each node | 16 |
| See connections to the server | 16 |
| Show server / cluster status | 17 |
| By running a query | 18 |



| Stopping existing statements | 18 |
|---------------------------------|----|
| Logs | 18 |
| Log file format: | 19 |
| Log rotation policy | 20 |
| Log Levels | 21 |
| Support Utilities | 21 |
| Report Collection | 21 |
| Export Reproducible Sample Data | 22 |



SQream DB Administrator Guide

Version 2019.2

Overview

This guide is intended for SQream DB administrators.

The guide will go through the DBA main tasks, as well as describing some of the best practices in SQream DB.

This guide is a complementary guide to the SQL Reference.

For further support please contact **support@sqreamtech.com** or your account manager.

Version 2019.2 - 5 - Administration Guide



Administration Guide

This document is mostly a conceptual overview and recommendations on best practices regarding SQream internal behavior. For SQL syntax and supported features, please refer to the SQL Reference Guide.

NOTE:

All keywords in are case insensitive.




Getting Started

Understanding the SQream DB environment

The SQream environment is usually made up of two folders - the installation directory and the storage cluster.

The installation directory

This folder contains the SQream DB binary applications.



The main applications found in the binary directory are:


| Executable Name | Description |
|-----------------|---|
| sqreamd | The sqreamd server daemon |
| ClientCmd | Command line client |
| upgrade_storage | Metadata storage upgrader to be used |
| | between versions |
| SqreamStorage | Storage utility to create new clusters and |
| | restore access |
| metadata_server | Metadata server for clustered installations |
| server_picker | Load balancer for clustered installations |

The storage cluster root

This directory contains the entire database storage.

Version 2019.2 - 7 - Administration Guide





| Directory | Description |
|------------|--|
| databases | The files containing all databases, tables, columns, chunks, etc. |
| metadata | Internal metadata structures for accessing data from disk |
| temp | Temporary spools |
| logs | The logs folder contains subfolders per SQream instance with folder name = [IP_port]. One folder per running SQream instance. |
| 127.0.0.1_ | Contains all logs files of a specific SQream instance |
| 5000 [IP_ | |
| port] | |

Setting up SQream DB

If you would like to deploy SQream DB on AWS or Azure please contact SQream directly at info@sqream.com.


Make sure that you are running on a 64-bit Linux operating system, and have an Nvidia GPU installed.

See the Hardware Requirements page to verify your system meets the minimum

Version 2019.2 - 8 - Administration Guide



requirements for running SQream DB.



Create the cluster

- 1. Enter the sqream directory and create a storage cluster
- 2. ./bin/SgreamStorage -C -r <full path to new cluster>

Example: Create storage cluster

```
If your main storage is on /mnt/storage, you can run
./bin/SqreamStorage -C -r /mnt/storage/sqream_storage
```

Configure the instances

Each SQream DB daemon must run against a configuration file.

Below is a sample minimal configuration file. It is recommended that it be placed in /etc/sqream_sqream_config.json. This file will start the server on port 5000, against GPU #0.

```
Example minimal configuration JSON

{
    "compileFlags": {
    },
    "runtimeFlags": {
    },
    "runtimeGlobalFlags": {
```



```
},
"server": {
    "licensePath" : "/etc/sqream/license.enc",
    "port": 5000,
    "cluster": "/mnt/storage/sqream_storage",
    "gpu": 0,
    "ssl_port": 5100
}
```

NOTE:

- JSON files can not contain any comments
- When altering the JSON file, pay close attention to the field-separating commas at the end of the lines.

Permanent instance options may be placed in this file, based on consultation with SQream support or through the configuration utility.

Configuring instances parameters

Table 20. Common parameters setting

| Flag Name | Description | Defau It Value | Range of Values | Remark |
|-------------------|-------------------|----------------------|--------------------|-----------|
| spoolmemorygb | Select what size | | 1- | Should |
| | spool SQream | 128gb | machine | consider |
| | DB can use for | | ram size | total ram |
| | writing | | | size and |
| | intermediate | | | number of |
| | results to RAM, | | | SQream |
| | in GB | | | instances |
| insertParsers | Set the number | 4 | 1-32 | Should |
| | of parsing | | | consider |
| | threads to be | | | total ram |
| | launched for | | | size and |
| | each file, during | | | number of |
| | the bulk load | | | SQream |
| | process | | | instances |
| insertCompressors | Set the number | 4 | 1-32 | Should |
| | of compression | | | consider |
| | threads to be | | | total ram |
| | launched for | | | size and |



| Flag Name | Description | Defau It Value | Range of Values | Remark |
|-------------------------------|---|----------------------|--------------------|---|
| | each file, during the bulk load process | | | number of SQream instances |
| statementLockTimeout | Set the number of seconds SQream will wait for a lock before returning an error | 3 | 1-no limit | |
| showFullExceptionInfo | Show complete error message | FALSE | TRUE/FAL SE | Enabling this setting will often show more detailed error message |
| initialSubscribedServi ces | List of services the instance will be subscribed to | sqrea m | list of strings | Example: "sqream,etl_ service,quer y_service" |
| useLogMaxFileSize | Defines whether SQream logs should be cycle every logMaxFileSize MB size | TRUE | TRUE/FAL SE | |
| logMaxFileSizeMB | Set the size of SQream logs cycle | 20 | >0 | Set in MB |

Starting and Stopping the SQream DB daemons

The procedure for starting and stopping the SQream DB daemons varies depending on your installation type:

- SQream based on Docker
- SQream based on RPM



SQream based on Docker

Use the start and stop options of the sqreamd command as described in the sqream-console commands in Start the SQream Console.

SQream based on RPM

A SQream RPM installation uses the Monit service to control the SQream services.

To start the SQream demons (Metadata, Server Picker and SQreamD):

```
$ sudo systemctl start monit
```

To check the SQream demons (Metadata, Server Picker and SQreamD):

Option 1:

```
$ sqream_status
```

Expected output:

```
SQreamDB monit.service: ACTIVE pid=6406 [ OK ]
SQreamDB metadataserver.service: ACTIVE pid=6427 [ OK ]
SQreamDB serverpicker.service: ACTIVE pid=6579 [ OK ]
SQreamDB sqream1.service: ACTIVE pid= 7440 [ OK ]
```

Option 2:

```
$ ps axuwww | grep -v 'grep\|tail\|monitor' | grep -i
'sqreamd\|metadata_server\|server_pick\|monit'
```

Expected output:

```
______
        7690 0.0 0.0 191916 2464 ? Ss 15:27 0:00
/bin/su - sqream -c /bin/nohup /usr/local/sqream/bin/metadata_
server &>> /var/log/sqream/metadataserver.log
sqream 7693 0.0 0.0 115304 1680 ? Ss 15:27 0:00 -
bash -c /bin/nohup /usr/local/sqream/bin/metadata server &>>
/var/log/sqream/metadataserver.log
sqream 7708 0.2 1.8 1110888704 183644 ? S1 15:27 0:02
/usr/local/sqream/bin/metadata server
/usr/local/sqream/bin/metadata_server root 8105 0.0 0.0 191916 2456 ? Ss 15:27 0:00
/bin/su - sqream -c exec /usr/local/sqream/bin/server picker
127.0.0.1 3105 &>> /var/log/sqream/serverpicker.log
sgream 8116 0.2 1.5 34887308 156592 ? Ssl 15:27 0:02
/usr/local/sqream/bin/server picker 127.0.0.1 3105
root 8450 0.2 0.0 131124 3452 ? Ssl 15:34 0:01
/usr/bin/monit -I
root 8453 0.0 0.0 191916 2460 ? Ss 15:34 0:00
/bin/su - sqream -c exec /usr/local/sqream/bin/sqreamd -config
/etc/sqream/sqream1\ config.json &>> /var/log/sqream/sqream1.log
```



```
sqream 8456 0.6 5.5 1111154756 542644 ? Ssl 15:34 0:04 /usr/local/sqream/bin/sqreamd -config /etc/sqream/sqream1_config.json
```

To stop all SQream services:

```
$ sudo /usr/local/sqream/config/sqream-stop.sh
```

Expected output:

```
==>Stopping SQreamDB Services
                  LOAD ACTIVE SUB DESCRIPTION
UNTT
  • metadataserver.service loaded Metadata Server For SQreamDB
  • serverpicker.service loaded Server Picker - Load Balancer For
    SQreamDB
  • sgream1.service loaded SQream SQL Server
LOAD = Reflects whether the unit definition was properly loaded.
ACTIVE = The high-level unit activation state, i.e. generalization of
     = The low-level unit activation state, values depend on unit
SUB
type.
3 loaded units listed. Pass --all to see loaded but inactive units, too.
To show all installed unit files use 'systemctl list-unit-files'.
==>SQreamDB Services have been stopped
._____
```

To stop a specific SQream service:

1. Stop the Monit service:

```
$ sudo systemctl stop monit
```

- 2. Stop the specific SQream service, for example stopping sqream1:
 - Option 1:

```
$ sudo systemctl stop sqream1
```

Option 2:

```
$ pkill -9 sqreamd
```

To restart a service that was stopped:

• Option 1:

Start the Monit service and monit will start all stopped services:



```
$ sudo systemctl start monit
```

• Option 2:

Start the stopped service manually:

```
$ sudo systemctl start sqream1.service
```

Connect to the SQream DB server with ClientCmd

To connect to the database server, you may use the ClientCmd command line interface by running

```
ClientCmd command line arguments
./bin/ClientCmd --user=<username> --password=<password> --
database=<database name> --host=<host> --port=<port> --
service=<service_name>
```

Connect to the master database:

```
Connecting to master on a local host running SQream DB on port 5000 via service 'etl_service'

./bin/ClientCmd --user=sqream --password=sqream --database=master --host=127.0.0.1 --port=5000 --service=etl_service
```

Using SSL Server Authentication with SQream

From version 2.1, SQream DB supports secure sockets layer (SSL) encryption and authentication for connections to its cluster via JDBC and ODBC drivers.

To use this option, the server must first be set-up to accept SSL connections.

Enabling SSL server authentication within SQream Instance:

Configure the SERVER flag ssl_port in the SQream instance configuration file to the needed port number.

For Example:

```
{
   "server":{
        "port": 5001,
        "ssl_port": 5100,
        "cluster": "/path/sqream_cluster",
        "gpu": 0,
        "licensePath": "/path/license.enc"
}
}
```



NOTE:

Restart the SQream DB daemons after making this configuration change

Configure SSL Authentication for JDBC/ODBC drivers Adding SSL to JDBC

- 1. Add ssl=true in the connection string
- 2. Change the port to the SSL port

NOTE:

When connecting via load balancer, the default endpoint for SSH is port 3109

Example for direct connection

jdbc:Sqream://hostname:5100/master;user=sqream;password=mypassword; ssl=true;

Example for connection to load balancer

jdbc:Sqream://hostname:3109/master;user=sqream;password=mypassword; service=sqream;cluster=true;ssl=true;

Adding SSL to ODBC

In Windows, make sure the SSL checkbox is selected in the DSN settings.

In Linux, add SsI=true to the connection string

Linux ODBC connection string sample

Driver=

{libODBCDrv.so}:Server=hostname:Port=5100:Database=master:User=sqre am:Password=mypassword:Ssl=true:Service=sqream

Highly available installations

Contact your SQream representative for further information about installing our highly available solutions.

Version 2019.2 - 15 - Administration Guide



Operations

Upgrading a version

Here are the necessary steps that ensure a smooth upgrade of your SQream DB version

- 1. Stop SQream instances on all servers
- 2. On each node that SQream is installed, unpack the new tarball alongside the old SQream DB directory.

 For example:

```
$ cd /home/sqream
$ mv sqream sqream-old
$ tar xf sqream-<version>.tar.gz
```

- 3. Repeat the above step for each node that the SQream DB executables exist
- 4. It may be necessary to run the metadata upgrade utility. (This may take a few moments)

```
$ cd sqream/bin
$ ./upgrade_storage <path to sqream storage cluster>
```

5. Restart the services

Key administration concepts

See Concepts above

Monitoring the system

Because SQream DB can be run in a distributed setting, all nodes should be monitored to ensure smooth operation. It is possible to monitor SQream DB with third party tools like Zabbix, Nagios and others, but also through the OS and SQream DB directly.

From the OS

See Identifying which SQream daemons are running

From each node

See connections to the server

You can monitor existing connections to the database by using the <code>show_connections()</code> utility function:



```
SELECT show_connections();
```

Table 21. Sample result from show connections ()

| ip | conn_id | conn_start_ time | stmt_id | stmt_start_ time | stmt |
|--------------|---------|------------------------|---------|------------------------|-----------------------------------|
| 192.168.0.93 | 19 | 2017-06-22 18:56:54 | 14 | 2017-06-22 18:56:54 | select show_ connections () |
| 192.168.0.93 | 17 | 2017-06-22 18:56:48 | -1 | 2017-06-22 18:56:48 | |

Show server / cluster status

The <code>show_server_status()</code> utility function can be used to see which statements are running across the cluster, across all databases.

NOTE:

If no queries are running, this query will return 0 rows in the result set.

```
SELECT show_server_status();
```

Table 22. Sample result from show server status()

| ser vic e_ id | conn ectio n_id | serv er ip | se rv er po rt | data bas e_ nam e | us e r_ na m e | clie nt ip | stat eme nt id | stat eme nt | stat eme nt star t time | state ment status | statem ent status start |
|------------------------|-----------------------|----------------------|----------------------------|-------------------------------|-------------------------------|---------------------|----------------------|--------------------|--|-------------------------|--|
| sqr ea m | 32 | 192.1 68.0. 93 | 50 00 | faa | sq re am | 192. 168. 0.1 | 25 | SELE CT Year | Carr ier | destCi tyNam e | COUNT (DISTIN CT originCi tyNam e) from ontime JOIN I_ airport_ i |



Possible statement status values

| Status | Description |
|-----------|---|
| Executing | The statement is in execution, awaiting results |
| Preparing | The statement is compiling, and is awaiting execution |
| Waiting | The statement is waiting in the queue for execution |

The DBA can use the show server status output as a baseline for identifying locks and if needed to stop running statements (based on the **server ip**: **server port** and **statement_id** columns).

By running a query

Running a query, even the most basic one, should give you an indication if a server is up. If you immediately get "Connection refused" or similar, the server is down.

Stopping existing statements

The **stop_statement()** utility function can be used to cancel or stop a running statement before it finishes.

Usage

- Identify the running statement ID and server IP and port (see show server status or show_connections above)
- From the same server/port combination run the stop_statement command:

```
SELECT stop_statement(42);
```

Logs

Each SQream instance generates its own set of log files based on the log rotation policy (see Log rotation policy). The files will be located in a dedicated folder (folder name contains IP and port).

For example: /home/sqream/sqream storage/sqreamdb/logs/127.0.0.1 5000.

TIP:

SQream recommends storing the log files in the shared storage so they can be all



analyzed in a single tool (e.g. SQream external table, Kibana etc.).

To generate an external table over the log files, use the command:

```
_____
create or replace external table t
( start message varchar(4),
  row id bigint,
  timestamp datetime,
  message level nvarchar(6),
  thread id nvarchar(40),
   ip nvarchar(15),
  port int,
   connection id int,
   db name nvarchar(128),
   user name nvarchar(128),
   statement id int,
   service name nvarchar(128),
   message type id int,
   message nvarchar(10000),
   end message varchar(5))
using format csv with path
'/home/sqream/sqream storage/sqreamdb/logs/*.log' field delimiter '|');
______
```

Log file format:

Delimited text format with the following column list:

- Row Id
- Timestamp
- Message Level
- Thread id
- IP
- Port
- Connection Id
- DB name
- User Id
- Statement Id
- Service name
- Message type id
- Message

Message type/contents:

| Message Type Code | Message Type | Message Content | Log level |
|----------------------|-------------------|-----------------|--------------|
| 1 | Statement started | Statement | Info |
| 2 | Statement | Statement | Info |



| Message Type Code | Message Type | age Type Message Content | | |
|----------------------|----------------------------|---|--------|--|
| | reconstruct | | | |
| 4 | Statement execution | "Executing" | Info | |
| 10 | Statement ended | "Success" / "Failed" | Info | |
| 20 | Compilation error | Error text | Info | |
| 21 | Execution error | Error text | Info | |
| 30 | Size | #MB | Info | |
| 31 | Result Set Rows | #records | Info | |
| 32 | Processed Rows | #records | Info | |
| 100 | Session started | Client IP address | Info | |
| 101 | Login "Success" / "Failed" | | Info | |
| 110 | Session ended | "Session ended" | Info | |
| 200 | Node info | Node info lines | Info | |
| 500 | Exception | Exception data | Error | |
| 1000 | Server startup | "Server startup" | System | |
| 1002 | Metadata | Metadata server location | System | |
| 1003 | Configuration | Configuration flags | System | |
| 1004 | STORAGE VERSION | storage version number | System | |
| 1010 | Server Error | Error message | fatal | |
| 1090 | Set config | Successful set config <flag_name> to value: <value></value></flag_name> | info | |
| 1100 | Server shutdown | Server shutdown | System | |

Log rotation policy

| Parameter | Description | Possible Values | Default Value | Comment |
|----------------------------|---|---|------------------|--|
| useLogMaxFileSize | Apply rotation based on log file size limit | TRUE / FALSE | FALSE | When set to 'TRUE' logRotateSizeMB configuration parameter is enabled. |
| logMaxFileSizeMB | Log file size in MB. | Integer between 1-1024 | 20 | |
| logFileRotateTimeFrequency | Frequency of log rotation | Daily Weekly Monthly Never | Never | Not case sensitive |



Log Levels

| Parameter | Description | Possible Values | Default Value |
|--------------------|-----------------------------------|-----------------|------------------|
| logClientLevel | Log level | 0 SYSTEM | 4 (INFO) |
| | | 1 FATAL | |
| | | 2 ERROR | |
| | | 3 WARNING | |
| | | 4 INFO | |
| nodeInfoLoggingSec | Theshold for writing from | Number to | 60 |
| | execution log to the instance log | represent | |
| | | seconds | |

Support Utilities

Report Collection

This support utility is used to collect logs and/or the leveldb at a client's site. The generated tar file can then be sent to the SQream support team for further investigation.

Output file format: report_[date]_[time].tar

Can run as a utility function or executable, allowing to collect information also if the SQream server is not running. Supported collection modes:

- log = only log files are collected
- db = only leveldb
- db_and_log = both log files and leveldb are collected

```
Syntax and example when running as a utility function:
```

```
SELECT report_collection('</pathToOutputFolder>', '<mode>');
SELECT report_collection('/home/sqream/log_collection','log'); )
```

Syntax and example for executable. The executable works only when no SQream instance is running:

```
./bin/report_collection <pathToSqreamDb> </pathToOutputFolder>
<mode>./bin/report_collection /home/sqream/sqream_storage/
/home/sqream/log collection log
```



Export Reproducible Sample Data

This support utility is used to collect data in order to reproduce a problematic query in a support lab (not only onsite at customer's site). Typically used for query issues that are data related. It runs a query, collects the data and stores the data in a small SQream DB (compressed into a single tar file). This file together with the query can be used in a remote system (support lab) to recreate and investigate the issue.

The output folder contains both the final tar file and data before its compression. It is sufficient to send the tar file. Works as utility function. No executable.

```
Syntax and example:
select export_reproducible_sample('</pathToOutputFolder>', 'sql
query1', 'sql query 2', ..);
select export_reproducible_sample('home/sqream/data_collection',
'select * from t');
```