TazMan-Audio

Fabric Reference

FABRIC

Table of contents

Introduction	4
Managers	5
Fabric Manager	6
Event Manager	7
Events	8
Event Listener	8
Event Trigger	9
Components	12
Component common properties	13
Runtime Parameter (RTP)	15
Audio Component	16
Dialog Audio Component	17
Group Component	18
Random Component	19
Sequencer Component	20
Switch Component	21
IntroLoopOutro Component	21
Volume meter component	22
Side chain Component	22
Loudness Meter Component	23
DSP Components	24
Timeline Component	26
Parameter properties	26
Layer properties	26
Region properties	27
Dynamic Mixer component	28
Preset properties	28

Fabric Reference


Utils	30
DebugLog	30
Asset Loader	31
Modular Synth Extension	32

Introduction


The Reference provides detailed information for all of the Fabric component properties.

Managers

The Fabric manager components can be accessed through the Component->Fabric menu selection.




Fabric Manager



Properties	Description	
Don't Destroy On Load	Allows the manager to stay alive when loading scenes	
Show All Instances	Shows all component instances in the hierarchy	
Enable Virtualization	Enable audio component to turn virtual (i.e. not playing) when listener is outside its max distance.	
Create Event Listeners	Automatically adds an event listener to all components either using the name or their full hierarchy path (if Use full path for name option is set)	
Enable Timeline Loader	Enables the automatic importing of timeline (*.fdp) projects located in the resources folder. It is possible to manually import an ftp project.	
Enable Debug Log	It will automatically add the DebugLog component for displaying Fabric error/warning/info messages	
Language	Allows setting the active language used by the DialogAudioComponent. (Use the Language window to create/edit language properties)	
Transition Threshold	Look ahead time (in ms) used by the sequence component to detect when to queue the next playlist entry in a sample accurate way	
AudioSource Pool		
Size	Determines the size of the pool. When 0 the pool is disabled	
Usage	Displays the number of sources currently in use	


Event Manager



Properties	Description
Log History Size	The size of the event log history (default: 128)
Force Queue All Events	Force queuing all posted events
Num of Events in Queue	Shows the number of events in the queue list
Clear Event List	Clears the event list
Add Event	The event with the name entered is added into the list.
Del Event	The event is deleted from the list.
Locate EventListeners	Highlights in the project hierarchy all game objects that have event listeners with a specific event name
Locate EventTriggers	Highlights in the project hierarchy all game objects that have event triggers with a specific event name

Events

The Event components can be accessed through the Component->Fabric->Events menu selection.



Event Listener




Properties	Description
Event Name	Name of the event to listen for.
Override Event Action	Enables/Disables event action override
Action To Override	Allow to override incoming event action

Fabric Reference

When the Action To Override is selected the following extra properties are added to the event listener

Properties	Description
Override on Specific Action	Enable event override on a specific event action
Old Event Action	Event action to override
New Event Action	Override with new event action. Most new event actions also allow to set new parameter values.

Event Trigger



Properties	Description
TriggerOn	When will the trigger occur:
	- Start
	- Destroy
	- Update
	- Enable
	- Disable
	- TriggerEnter
	- TriggerExit
	- CollisionEnter
	- CollisionExit
	- MouseUp
	- MouseDown
	- MouseOver
	- MouseExit
Action	The action to be taken when the event is received:
	- PlaySound
	- StopSound
	- PauseSound

Fabric v2.1.7

	- UnpauseSound	
	- SetVolume	
	- SetPitch	
	- SetSwitch	
	- SetParameter	
	- SetFadeIn	
	- SetFadeOut	
	- SetPan	
	- AddPreset	
	- RemovePreset	
	- SetDSPParameter	
	- RegisterGameObject	
	- ResetDynamicMixer	
	- AdvanceSequence	
	- ResetSequence	
	- SwitchPreset	
	- SetTime	
	- SetModularSynthParameter	
Delay (secs)	Delays the event trigger by the time set in seconds	
Probability (%)	Defines the percentage of the event trigger happening.	
Ignore GameObject	Game Object is not used with the event (no 3D position update)	
Add To Queue	Adds the event to a queue for processing when the event manager	
	update is called	
Override Parent	Allows to override the game object used by default (i.e. the game	
GameObject	object that has the event trigger)	
Trigger Event	Force a trigger of the event.	

When the Set DSPParameter action is selected the following extra properties are added to the event trigger

Properties	Description
Value	The value of the DSP effect set according to its range
Time	Time it will take for the DSP parameter to reach this value
Curve	The interpolation curve (0.5=Linear, Log < 0.5 > Exp)

The "Set DSPParameter" supports the following DSP effect parameters

DSP	Parameter	Description
Low Pass		
	Cutoff Frequency	Lowpass cutoff frequency in hz. 10.0 to 22000.0. Default
	Lowpass Resonance Q	Lowpass resonance Q value. 1.0 to 10.0. Default = 1.0.
High Pass		
	Cutoff Frequency	Highpass cutoff frequency in hz. 10.0 to 22000.0. Default
	Highpass Resonance Q	Highpass resonance Q value. 1.0 to 10.0. Default = 1.0.


Fabric v2.1.7

Fabric Reference

Echo		
	Delay	Echo delay in ms. 10 to 5000. Default = 500.
	Decay Ratio	Echo decay per delay. 0 to 1. 1.0 = No decay, 0.0 = total decay (ie simple 1 line delay). Default = 0.5.L
	Wet Mix	Volume of echo signal to pass to output. 0.0 to 1.0. Default = 1.0.
	Dry Mix	Volume of original signal to pass to output. 0.0 to 1.0. Default = 1.0.
Distortion		
	Distortion	Distortion value. 0.0 to 1.0. Default = 0.5.
Chorus		
	Dry Mix	Volume of original signal to pass to output. 0.0 to 1.0. Default = 0.5.
	Wet Mix 1	Volume of 1st chorus tap. 0.0 to 1.0. Default = 0.5.
	Wet Mix 2	Volume of 2nd chorus tap. This tap is 90 degrees out of phase of the first tap. 0.0 to 1.0. Default = 0.5.
	Wet Mix 3	Volume of 3rd chorus tap. This tap is 90 degrees out of phase of the second tap. 0.0 to 1.0. Default = 0.5.
	Delay	The LFOs' delay in ms. 0.1 to 100.0. Default = 40.0 ms
	Rate	The LFOs' modulation rate in Hz. 0.0 to 20.0. Default = 0.8 Hz.
	Depth	Chorus modulation depth. 0.0 to 1.0. Default = 0.03.
	Feed Back	Chorus feedback. Controls how much of the wet signal gets fed back into the filter's buffer. 0.0 to 1.0. Default = 0.0.

Components

Several components each with its own functionality can be added into a game object by selecting them from the Fabric->Components menu selection.



Component common properties

▼ C			
▼ Component Properties			
Max Instances:			
AllowMultipleObjectInst:	▼		
Priority:	•		
Stealing Mode:	Oldest	‡	
Override Fade Properties			
FadeInTime:			
FadeInCurve:		0.5	
FadeOutTime:			
FadeOutCurve:			
Override Volume		0.5	
Volume:	•		
Volume Rand:	<u>-</u>		
Override Pitch			
Pitch:	•		
Pitch Rand (+/-):	•		
Override 2D Properties	₹		
Pan2D:	·		
Override 3D Properties	▼		
Pan Level:			
Spread Level:	•		
Doppler Level:			
Min Distance:			
Max Distance:	500		
RolloffMode:	Logarithmic		
Component is:			
	Node Info		
Instances: 0 (1)			
Volume: 1			
Volume offset: 0 Fade: 1.00(1.00)			
Pitch: 1			
Pitch offset: 0			
Status: [Stopped]			
CPU: 0.000ms (Max:0.000ms)			
er o. o.oooms (Max:0.00			
Drag and Drop AudioClips here to automatically create Audio Components			
(Use the	e inspector lock option to maintain focus)		
Create type of: Audio	Component		

Fabric Reference


Properties	Description
Max Instances	Number of maximum instances that can be played. Note: Only used
	when the component has an Event Listener attached to it and
	therefore can be triggered.
Priority	Determines how important this component is.
Stealing	Stealing behaviour when max instances is reached:
	- Oldest - Newest
	- Newest - Farthest
	- None
FadeInTime	Sets the fade in time of this node
FadeInCurve	Sets the fade in curve type (0.5 = linear, log < 0.5 > Exp
FadeOutTime	Sets the fade out time of this node
FadeOutCurve	Sets the fade out curve type (0.5 = linear, log < 0.5 > Exp
Override Parent Volume	Overrides the parent volume.
Volume	Volume of the component multiplied with its parent volume.
Volume Randomization	Amount of volume randomization to be added.
Override Parent Pitch	Overrides the parent pitch. (If not top node)
Pitch	Pitch value of the component multiplied with its parent pitch.
Pitch Randomization	Amount of pitch randomization to be added.
Override 2D Properties	Override parent 2D properties. (If not top node)
Pan2D	Sets a channel pan position linearly. Only works on 2D clips.
Override 3D Properties	Override parent 3D properties. (If not top node)
Pan Level	Sets how much the 3D engine has an effect on the component.
Spread Level	Sets the spread angle a 3D stereo or multichannel sound.
Doppler Level	Sets the Doppler level of the component.
Min Distance	Min audible distance.
Max Distance	Max audible distance.
Rolloff Mode	Determines how fast the sounds fades over distance:
	- Logarithmic
	- Linear
	- Custom
Component is	Shows the status of the component
	- Active - Inactive
	- inactive

Runtime Parameter (RTP)




Properties	Description
Property	Component property that parameter will control - Volume - Pitch - Pan 2D - Pan Level - Spread Level - Doppler Level - Priority
Parameter	The parameter name that will listen for a value from the game through the API or as an event listener component.
Loop	If the Speed properties is set then the parameter will loop according to the behaviour selected. - One Shoot - Loop - Ping Pong
Min	The min value of the parameter
Max	The maximum value of the parameter
Seek	The parameter will seek to the target at the specified rate
Speed	The parameter will advance at a specified rate

Audio Component



Properties	Description
Ignore Virtualization	Audio component won't be virtualized (stopped) according to
	distance from listener.
Don't Play	Audio component won't play.
Delay	How much to delay (is seconds) the component from playing
Don't Stop On Destroy	Keeps playing when it's parent game object is destroyed. The last know position of the game object is used.
Loop	Pitch value of the component multiplied with/by its parent pitch.
Audio Clip	Audio clip to play.
Status	Displays the current status of the audio component - WaitingToPlay - Playing - WaitingToStop - Stopped - Paused - Virtual - LostFocus

Dialog Audio Component



Properties	Description
Audio Clip Reference	Name of the audio clip to play

Note: Dialog Audio component provides the same properties as the standard Audio Component.

Group Component




Properties	Description
Volume	Set volume for all children components.
Pitch	Set pitch for all children components.
Mute	Mutes all children components.
Solo	Mutes all other group components except this one.

Random Component



Properties	Description
Play Mode	The type of playing mode: - Random: Elements are picked in random RandomNoRepeat: Elements picked at random but are not repeated.
Weight	In random mode allows to set the weight of an entry making it play more often.


Sequencer Component



Properties	Description
Sequence Type	The type of the sequence: - PlayContinuous: Plays all elements in sequence PlayOnAdvance: Advances on the next element when is triggered again.
Advance On	If PlayOnAdvance type is selected the following advance options become available: - AdvanceSequenceEventAction: Will advance to the next entry when the EventAction.AdvanceSequence is received. - PlayEventAction: Will advance to the next entry when an EventAction.PlaySound is received.
Play Mode	The playing mode determines if a sequence is repeated or not. - Single: Plays sequence one and then stops. - Loop: Plays sequence continuously.
Transition Offset (sec)	Offset that allows overlapping by trigger the next entry in the sequence earlier (-) or later (+).
Transition Offset Rand (sec)	Applies a random value within this range on top of the transition offset
Playlist	The order in which the sequence will play its sub-components. Note: In AdvanceSequenceEventAction mode the option "PlayToEnd" is available on each entry and when set the sequence will wait until the end of the current entry has been reached before advancing into the next.

An arrow (←) indicates which component is currently playing.

Switch Component



Properties	Description
Start On Switch	Starts the component playing when a switch occurs.
Switch Type	The switch types available: - SwitchOnPlay - SwitchOnEnd - SwitchOnSwitch
Component	Currently selected component. Use this to select the default component.

IntroLoopOutro Component




Properties	Description
Intro	Intro entry will play first
Loop	Loop plays immediately after intro
PlayLoopToEnd	If enabled it will wait to reach the end of the loop before it moves to the outro stage
Outro	Outro will play only when the component is stopped

Volume meter component



Properties	Description
Is3D	Sets if the audio sources in the hierarchy are 3D.
	NOTE: This will be removed in future versions

Side chain Component



Properties	Description
Gain (dB)	Controls the input gain coming from the volume meter
Attack (secs)	Defines how fast the side chain will respond to a positive input value
Release (secs)	Defines how fast the side chain will respond to a negative input value


Loudness Meter Component




Fabric Reference

DSP Components


Audio Panner



Chorus Filter



Distortion Filter



Echo Filter




Fabric Reference

High Pass Filter



Low Pass Filter



Note: Refer to the event trigger section for DSP properties and value ranges.


Timeline Component

Parameter properties



Properties	Description
Name	The name of the parameter
Loop	If the Speed properties is set then the parameter will loop according to the behaviour selected. - One Shoot - Loop - Ping Pong
Min	The min value of the parameter
Max	The maximum value of the parameter
Seek	The parameter will seek to the target at the specified rate
Speed	The parameter will advance at a specified rate


Layer properties



Properties	Description
Name	The name of the layer
Volume	Sets the layer volume
Mute	Mutes the layer
Control Parameter	The parameter that controls the layer


Fabric v2.1.7

Region properties



Properties	Description		
Name	The name of the region		
Х	The start position of the region in the timeline		
Width	The length of the region in the timeline		
Autopitch	The region pitch is linearly scaled up or down relative to the centre of the region		
Autopitch Base	Used for fine tuning the auto pitch value		
On Exit	This option determines how the region will behave when a parameter exists - Keep Playing		
	- Play To End - Cutoff		

Dynamic Mixer component



Properties	Description
AutoAddGroupComponents	Flag that automatically adds/removes group components (NOTE: Disabled for the first v2.0 release)
Create	Creates a preset with a given name
Del	Deletes the preset
AddPreset	Adds preset to the active list
RemovePreset	Removes preset from the active list


Preset properties



Properties	Description
Is Persistent	If its ticked the preset won't be removed when the dynamic mixer reset function is called through the event system or API
Activate on Event	Preset will automatically get activated when the event is posted and will remain active for the duration of the event.
GameObject	GameObject used when checking if an event is active

Fabric v2.1.7


GroupPreset




Properties	Description	
Group Component	The group component to be modified	
Volume	Volume to set in dB	
Pitch	Pitch to set	
FadeInTime	The time it will take to reach the volume/pitch values, in seconds	
FadeInCurve	The type of transition curve (0.5 = linear, log < 0.5 > exp	
FadeInTime	The time it will take to remove the volume/pitch values, in second	
FadeInCurve	The type of transition curve (0.5 = linear, log < 0.5 > exp	

Utils

Fabric comes with helper components which can be found in the Fabric->Utils menu selection.




DebugLog




Properties	Description
Break On Error	Stops execute of code if an error occurs.
Enable Errors	Enables errors to be handled.
Enable Warnings	Enables warnings to be handled.
Enable Infos	Enables infos to be handled.


Asset Loader



Properties	Description
Prefab Assets	List of prefab assets to be loaded/unloaded.

Modular Synth Extension





▼ Modular Synth Graph Unity (Script)		₽ \$,
	Clear graph	
Script	■ ModularSvnthGraphUnitv	
▼Module Info List		
Size		
▶IO/Input ▶IO/Output ▶Filter/LowPassFilter ▶Panel/FloatSlider ▼Module Link Info List		
Size		
⊳f82a942f-9f66-4d3c-aa ⊳bbb72924-bc82-413e- ⊳f150231a-10c0-4699-a	8951-7af64b93de02	

