

ANDROID SDK V3.2.2

Contents

Introduction	3
Supported Channels	3
Prerequisites	3
Download the SDK	4
The Flow	4
Integrating the SDK	5
Class and Interface	6
Initialization	7
Callback	8
Executing Payment	11
Other Important Methods	12
SDK Build	13
Queries	13

Introduction

Mimopay Android SDK is designed to help you, as a developer, or your developer team to integrate your android application or games to Mimopay's payment service. Mimopay Android SDK is equipped with an easy-to-understand User Interface and also easy to integrate.

Supported Channels

Topup:

- 1. Smartfren
- 2. Sevelin

ATM:

- 1. BCA
- 2. Bersama

Telkomsel Upoint:

- 1. Airtime
- 2. HRN (Voucher)

XL:

- 1. Airtime
- 2. HRN (Voucher)

Maxis:

1. Airtime

Digi:

1. Airtime

Celcom:

1. Airtime

Vietnam Telco:

- 1. VinaPhone
- 2. MobiFone
- 3. Viettel

Indosat:

1. Airtime

Prerequisites

Before you begin, you need to make sure that you are a registerred merchant at Mimopay payment gateway since the SDK will be useless without user ID, merchant code, and secret key that required to pass at initialization


Download the SDK

The SDK is available at https://github.com/mimopay/Mimopay-Android-SDK. You can clone it with whatever git tool you have or use command line as shown below

git clone https://github.com/mimopay/Mimopay-Android-SDK.git

The Flow

UI Mode Flow Illustration



Where:

- (a) User choose to do some payment.
- (b) Merchant's app to activate SDK's built-in UI. In this stage, merchant's app is become inactive. All interaction only between user and the SDK. The SDK provides necessary UI controls to simplify user to do the payment
- (c) User choose some payment channel and method
- (d) The SDK's UI pass all necessary things that user has choosen or input, to mimopay server
- (e) Mimopay server replies back the results
- (f) The SDK display the results
- (g) Mimopay server than apply callback to merchant's server

Integrating the SDK

Before you start, you need to follow these steps below

- 1. You need to copy the Mimopay.jar into libs directory of your project.
- 2. The SDK require several android permissions so you need to add lines of codes below into the AndroidManifest.xml file of your project

```
<uses-permission android:name="android.permission.INTERNET" />
<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE" />
<uses-permission android:name="android.permission.READ PHONE STATE" />
<uses-permission android:name="android.permission.SEND_SMS"/>
<uses-permission android:name="android.permission.READ_SMS" />
```

3. You need to add several line of codes below into the AndroidManifest.xml file of your project

```
<activity
       android:name="com.mimopay.MimopayActivity"
       android:theme="@android:style/Theme.Translucent.NoTitleBar.Fullscreen"
       android:windowSoftInputMode="stateUnspecified|adjustPan"
</activity>
```

4. You also need to add these three line of codes into your java source.

```
import com.mimopay.Mimopay;
import com.mimopay.MimopayInterface;
import com.mimopay.merchant.Merchant;
```

Class and Interface

The following is the description of the SDK class and interface that you have imported in your java source code

```
public class Mimopay {
       public Mimopay(Context context,
               String emailOrUserId, String merchantCode, String productName,
               String transactionId, String secretKey, String currency,
               MimopayInterface mimopayinterface
       )
       // Topup
       public void executeTopup(String channel)
       // ATMs
       public void executeATMs(String channel)
       // Telkomsel Upoint
       public void executeUPointHrn()
       public void executeUPointAirtime()
       public void executeUPointAirtime(String amount)
       // XL
       public void executeXLAirtime()
       public void executeXLHrn()
       public void executeXLAirtime(String amount)
       // Maxis
       public void executeMPointAirtime()
       public void executeMPointAirtime(String amount)
       // Digi
       public void executeDPointAirtime()
       public void executeDPointAirtime(String amount)
       // Celcom
       public void executeCelcomAirtime()
       public void executeCelcomAirtime(String amount)
       // Vietnam Telco
       public void executeVnTelco()
       // Indosat
       public void executeIndosatAirtime()
       public void executeIndosatAirtime(String amount)
       // General functions
       public String getSdkVersion()
       public void enableGateway(boolean enable)
       public void enableLog(boolean enable)
       public String[] getLastResult()
       public void setCurrency(String currency)
}
public interface MimopayInterface {
       public void onReturn(String info, ArrayList<String> params);
```

Initialization

The SDK initialization require you to fill all your merchant stuffs into its parameters. Please refer to http://staging.mimopay.com/api.

```
Mimopay mimopay = new Mimopay(
       Context context,
                                      // your android application context
       String emailOrUserId,
       String merchantCode,
       String productName,
       String transactionId,
       String secretKeyStaging,
       String secretKeyGateway,
       String currency,
       MimopayInterface mi
                                     // your callback interface
);
```

transactionId may set to empty (transactioID = "") which cause the library to generate a unique value based on unix timestamp.

In the sample source codes, the secretKeyStaging and secretKeyGateway is managed as string of encrypted keys.

```
try {
   secretKeyStaging = Merchant.get(true, "zLdLLbLX7xi2E4zxcbGMPg==");
   secretKeyGateway = Merchant.get(false, "5aSkczdhkk4ukFsZEHykkA==");
} catch(Exception e) {
}
```

The encrypted values are bundled in a java JAR file that should be placed in the lib directory along with the SDK jar to make the final build. This will allow you to avoid your secretKey written in your java source codes.

Please contact us and we will generate for you a text file (encrypted keys) and JAR file (encrypted values).

Callback

To obtain any information from the SDK during and after execution, you need to use MimopayInterface interface and override its oReturn method as decribed below.

```
MimopayInterface mimopayinterface = new MimopayInterface()
{
       public void onReturn(String info, ArrayList<String> params)
               if(info.equals("SUCCESS")) {
                       // do what you want to do
               } else if(info.equals("ERROR")) {
                       // do what you want to do
               } else if(info.equals("FATALERROR")) {
                       // do what you want to do
               }
};
```

Use 'info' as indicator whether it is success, error, or fatal error status. Use 'params' to obtain the details. Be noticed that 'params' may set to **null** so you need to test first whether it equal to null or not. After that, you should obtain its size. Here is the ilustration

```
if(params != null) {
        int j = params.size();
        // ....
```

The following table visualize on Return's info and params string

Info		Params	Meaning	
	0	UserCancelled	User was cancelling the transaction	
	0	MerchantLoadUrlNull	You pass the channel string other than listed in this document	
	0	ErrorConnectingToMimopayServer	Internet connection problem	
	0	ErrorValidatingVoucherCode	Occurs when SDK receive other then 'ok' status from server in during transaction process	
	0	ErrorInternetConnectionProblem	Internet connection problem	
	0	UnsupportedPaymentMethod	Requested payment method does not exist	
	0	Unspecified Channel Request	Requested payment channel does not exist	
ERROR	0	ErrorHTTP404NotFound	Server return 404 error code.	
	0	ErrorUnderMaintenance	The current payment channel is under maintenance	
	0	ErrorInvalidPhoneNumber	Phone number that you've supplied is in invalid format	
	0	ErrorInvalidDenomValue	The denom value that you've supplied is in invalid format	
	0	ErrorInvalidAmountValue	The amount value that you've supplied is in invalid format	
	Notes: Those error listed above are errors that occurs during transaction process. Since all transactions are done by Mimopay's server and also depend on the input, at the end of transaction, server might return an error or failed. Therefore since it is considerred as the end of the transaction (not 'during' transaction), then SDK will always return SUCCESS once it received status=200. In other word, the transaction success but the result is failed/error.			
SUCCESS	03			
FATALERROR	0	Depends on the uncaughtException message	Occurs when the SDK suddenly force closed by the Android OS	

Payment Method	info	params			
		0	1	2	3
	SUCCESS	smartfren	OK	Sukses	
Smartfren		smartfren	FAILED	*SF1	
	ERROR	LE	*HST	*JEM	
	CHCCECC	sevelin	OK	Sukses	
Sevelin	SUCCESS	sevelin	FAILED	*SV1	
	ERROR	LE	*HST	*JEM	
ATM DCA	SUCCESS	atm_bca	*AT1	*AT2	*AT3
ATM BCA	ERROR	LE	*HST	*JEM	
ATN 4 D	SUCCESS	atm_bersama	*AT1	*AT2	*AT3
ATM Bersama	ERROR	LE	*HST	*JEM	
	CHOOLCC	upoint_hrn	OK	Sukses	
Upoint HRN (voucher)	SUCCESS	Upoint_hrn	FAILED	*SF1	
	ERROR	LE	*HST	*JEM	
	SUCCESS	upoint_airtime	*UP1	*AT1	*AT2
Upoint Airtime	ERROR	LE	*HST	*JEM	
,	ERROR	LE	*HST	*JEM	
	SUCCESS	xI airtime	*XL1	*AT1	*AT2
XL Airtime	ERROR	LE	*HST	*JEM	
	ERROR	LE	*HST	*JEM	
		xl hrn	OK	Sukses	
XL HRN (voucher)	SUCCESS	xl hrn	FAILED	*XV1	
	ERROR	LE	*HST	*JEM	
	SUCCESS	mpoint_airtime	OK	*AT2	
Maxis Airtime	ERROR	LE	*HST	*JEM	
	ERROR	LE	*HST	*JEM	
	SUCCESS	dpoint_airtime_charge	OK	*AT2	
Digi Dpoint	ERROR	LE	*HST	*JEM	
	ERROR	LE	*HST	*JEM	
	SUCCESS	celcom_airtime	ОК	*AT2	
Celcom	ERROR	LE	*HST	*JEM	
	ERROR	LE	*HST	*JEM	
VnTelco	2	topup_vn	OK	Success	
	SUCCESS	topup_vn	FAILED	*VT1	
	ERROR	LE	*HST	*JEM	
	SUCCESS	indosat_airtime	*IS1	*AT1	*AT2
Indosat Airtime	ERROR	LE	*HST	*JEM	AIZ
muusat All tiine	ERROR	LE	*HST	*JEM	

Empty cell on params column means equals to **null** LE = Listed Errors. Please refer to previous table * = Please refer to table below

SF1	Kode voucher sudah digunakan (voucher code has been used already)
VT1	Failed
SV1	Kode Voucher salah (wrong voucher code)
AT1	Company Code
AT2	Total Amount
AT3	Transaction ID
UP1	6-digit UP Code (upoint)
AT1	Destination Number for the for sending the shortcode
AT2	User phone number
XL1	4-digit XL's shortcode
XV1	Reload Gagal
MP1	You will receive a sms soon, please follow the instruction in it to complete this payment
DG1	SMS CODE is comming in
HST	Http status code or Java Exception (-1)
JEM	Java Exception status
IS1	Keyword BELI followed by 3 digit shortcode

Executing Payment

The following table will help you to understand the SDK's methods and how they are categorized.

Pymt Method	Channel	Built-in UI
Торир	smartfren sevelin	• void executeTopup(String channel)
ATM	atm_bca atm_bersama	void executeATMs(String channel)void executeATMs (String channel, String amount)
Telkomsel	upoint upoint_hrn	 void executeUPointHrn() void executeUPointAirtime() void executeUPointAirtime(String amount)
XL	xl_airtime xl_hrn	void executeXLAirtime()void executeXLAirtime(String amount)void executeXLHrn()
Maxis	mpoint	void executeMPointAirtime()void executeMPointAirtime(String amount)
Digi	dpoint	void executeDPointAirtime()void executeDPointAirtime(String amount)
Celcom	celcom	void executeCelcomAirtime()void executeCelcomAirtime(String amount)
Vietnam Telco	vnp (VinaPhone) vms (MobiFone) vte (Viettel)	void executeVnTelco()
Indosat	Indosat_airtime	 void executeIndosatAirtime() void executeIndosatAirtime(String amount)

For Airtime payment methods, the SDK has its ability to allow user to send telco's shortcode SMS automatically however, it still need user intervention by showing a dialog message window to allow user to type the shortcode.

Parameter explanation:

String channel

```
channel should be one of the followings
```

```
smartfren
sevelin
atm bca
atm bersama
upoint
upoint hrn
xl airtime
xl hrn
mpoint
dpoint
celcom
topup vn
indosat_airtime
```

String code

A voucher code string for smartfren, sevelin, xl hrn, and upoint hrn topup

String amount

A mimocard value for atm bca & atm bersama

Other Important Methods

- For some reason you may want to know the current SDK version. You may call getSdkVersion() to obtain the current SDK version
- By default, the SDK points to staging.mimopay.com during execution. On your production release, you should use gateway.mimopay.com instead of staging. To enable it you call enableGateway(boolean enable) with enable sets to true
- The last successful transaction always be recorded. You can call getLastResult() to obtain those transaction messages.
- Sometimes we need to visualize SDK's log activities during process. You may enable it by calling enableLog(boolean enable) with enable sets to true
- Since version v2.2 SDK's built-in UI is now support custom language. Please refer to CustomLang.java source code, it shows you how to manage all words of your desired language in a single array of strings. After that then you need to call setUiLanguage(String[] slang)

SDK Build

The SDK builds with Android API Level 21

Queries

If you have any queries or issues please email me at jimmy@mimopay.com or skype to <u>jimmybas</u>