# Radioactive Binding SOP

# Talia Albert

# June 27, 2024

# Contents

1	$\mathbf{Pre}$	paration	2
2	Ben 2.1 2.2 2.3	Ach Work Preparation	2 2 2 2
3	Dat	a Submission	2
4	4.1 4.2 4.3 4.4 4.5	Log Book essientals Calculations Examples 4.3.1 Example 1 4.3.2 Example 2 4.3.3 Example 3 4.3.4 Example 4 Chart 4.4.1 Quick trick to calculate Dry Waste Finishing a hot ligand	2 2 2 3 3 4 5 6 7 7 8
5	<b>For</b> 5.1	mulas & Calculations         uCi & uL Needed          5.1.1 Need          5.1.2 Formula          5.1.3 Where	8 8 8 8

# 1 Preparation

- 2 Bench Work
- 2.1 Preparation
- 2.2 Adding to drug plate
- 2.3 Filtering
- 3 Data Submission

## 4 Book Keeping

How do we sign out the log book?

### 4.1 Log Book essientals

The online system is only sensitive enough to record 0.001 mCi for sink waste or dry waste. Even though we calculate how much mCi we need for assay's usually to 0.00001 (for example, 8.32 uCi = 0.00832 mCi, which we round up to 0.009 mCi) There are 3 values which needed to be recorded.

- Total mCi removed from vial
- mCi disposed down sink (80% of Total mCi removed, called sink waste)
- mCi disposed through **dry** waste (20% of Total mCi removed, called *dry waste*)

$$Total mCi = Sink Waste + Dry Waste$$

#### 4.2 Calculations

- 1. When calculating the **Total mCi** removed from the vial, always round total mCi up to the nearest 0.001 mCi.
- 2. Calculate the **Dry Waste** by

Dry Waste = Total 
$$mCi * 0.2$$

always round Dry Waste down to the nearest 0.001 mCi

3. Calculate **Sink Waste** by

$$Sink Waste = Total mCi - Dry Waste$$

The *minimum* value for sink waste and dry waste is 0.001 mCi, therefore the minimum value for the Total mCi removed from the vial is 0.002 mCi.

### 4.3 Examples

#### 4.3.1 Example 1

0.94 uCi Pyrilamine used

- 1. Convert units from uCi to mCi, 0.94 uCi to 0.00094 mCi
- 2. Determine **Total mCi**, round up to nearest 0.001 mCi,

Total mCi = 
$$0.00094$$
 mCi  $\rightarrow 0.001$  mCi

but, the minimum value for the Total mCi removed from the vial is 0.002 mCi

Total mCi = 
$$0.001$$
 mCi  $\rightarrow 0.002$  mCi

Total mCi	Sink Waste	Dry Waste
0.002		

#### 3. Determine **Dry Waste**

Dry Waste = **Total mCi** \* 
$$0.2 = 0.002 * 0.2 = 0.0004$$

always round Dry Waste down to the nearest 0.001 mCi

Dry Waste = 
$$0.0004 \to 0.000$$

but the *minimum* value for sink waste and dry waste is 0.001 mCi,

Dry Waste = 
$$0.000 \to 0.001$$

Total mCi	Sink Waste	Dry Waste
0.002		0.001

#### 4. Determine the Sink Waste

Sink Waste = Total mCi - Dry Waste = 
$$0.002 - 0.001 = 0.001$$

Total mCi	Sink Waste	Dry Waste
0.002	0.001	0.001

#### 4.3.2 Example 2

#### 2.58 uCi PK11195

- 1. Convert units from uCi to mCi, 2.58 uCi to 0.00258 mCi
- 2. Determine **Total mCi**, round up to nearest 0.001 mCi,

Total mCi = 0.00258 mCi  $\rightarrow 0.003$  mCi

Total mCi	Sink Waste	Dry Waste
0.003		

#### 3. Determine **Dry Waste**

Dry Waste = Total mCi 
$$* 0.2$$

Dry Waste = 
$$0.003 * 0.2$$

Dry Waste 
$$= 0.0006$$

always round Dry Waste down to the nearest 0.001 mCi

Dry Waste = 
$$0.0006 \rightarrow 0.000$$

but the *minimum* value for sink waste and dry waste is 0.001 mCi,

Dry Waste = 
$$0.000 \to 0.001$$

Total mCi	Sink Waste	Dry Waste
0.003		0.001

#### 4. Determine the Sink Waste

$$Sink Waste = Total mCi - Dry Waste$$

Sink Waste = 
$$0.003 - 0.001$$

Sink Waste 
$$= 0.002$$

Total mCi	Sink Waste	Dry Waste
0.003	0.002	0.001

#### 4.3.3 Example 3

#### 8.64 uCi Citalopram

- 1. Convert units from uCi to mCi, 8.64 uCi to 0.00864 mCi
- 2. Determine **Total mCi**, round up to nearest 0.001 mCi,

Total mCi = 0.00864 mCi  $\rightarrow 0.009$  mCi

Total mCi	Sink Waste	Dry Waste
0.009		

#### 3. Determine **Dry Waste**

Dry Waste = Total 
$$mCi * 0.2$$

Dry Waste = 
$$0.009 * 0.2$$

Dry Waste 
$$= 0.0018$$

always round Dry Waste down to the nearest 0.001 mCi

Dry Waste = 
$$0.0018 \to 0.001$$

Total mCi	Sink Waste	Dry Waste
0.009		0.001

#### 4. Determine the Sink Waste

$$Sink Waste = Total mCi - Dry Waste$$

Sink Waste = 
$$0.009 - 0.001$$

Sink Waste 
$$= 0.008$$

Total mCi	Sink Waste	Dry Waste
0.009	0.008	0.001

Total mCi	Sink Waste	Dry Waste
0.034		

#### 4.3.4 Example 4

33.62 uCi GR125743

- 1. Convert units from uCi to mCi, 33.62 uCi to 0.03362 mCi
- 2. Determine **Total mCi**, round up to nearest 0.001 mCi,

Total mCi = 
$$0.03362$$
 mCi  $\rightarrow 0.034$  mCi

#### 3. Determine **Dry Waste**

Dry Waste = Total mCi 
$$* 0.2$$
  
Dry Waste =  $0.034 * 0.2$   
Dry Waste =  $0.0068$ 

always round Dry Waste down to the nearest 0.001 mCi

Dry Waste = 
$$0.0068 \to 0.006$$

Total mCi	Sink Waste	Dry Waste
0.034		0.006

#### 4. Determine the Sink Waste

Sink Waste = Total mCi 
$$-$$
 Dry Waste Sink Waste =  $0.034 - 0.006$  Sink Waste =  $0.028$ 

Total mCi	Sink Waste	Dry Waste
0.034	0.028	0.006

#### 4.4 Chart

The following chart contains the associated sink waste and dry waste values for Total mCi values from 0.002 to 0.026.

Total mCi	Sink Waste	Dry Waste
0.002	0.001	0.001
0.003	0.002	0.001
0.004	0.003	0.001
0.005	0.004	0.001
0.006	0.005	0.001
0.007	0.006	0.001
0.008	0.007	0.001
0.009	0.008	0.001
0.010	0.008	0.002
0.011	0.009	0.002
0.012	0.010	0.002
0.013	0.011	0.002
0.014	0.012	0.002
0.015	0.012	0.003
0.016	0.013	0.003
0.017	0.014	0.003
0.018	0.015	0.003
0.019	0.016	0.003
0.020	0.016	0.004
0.021	0.017	0.004
0.022	0.018	0.004
0.023	0.019	0.004
0.024	0.020	0.004
0.025	0.020	0.005
0.026	0.021	0.005

#### 4.4.1 Quick trick to calculate Dry Waste

You may notice that every 0.005, the Dry Waste increases by 0.001. You can quickly determine the Dry waste values of larger numbers by looking for the nearest multiple of 0.005 that is less than or equal to the Total mCi number. For example, 0.048 mCi total waste, 0.045 is the nearest multiple of 0.005, and 9\*0.005 = 0.045 therefore, the dry waste value is 0.009.

### 4.5 Finishing a hot ligand

### 5 Formulas & Calculations

### 5.1 uCi & uL Needed

#### 5.1.1 Need

• Specific Activity (Ci/mmol) (S.A.)

- Assay Conc (nM)
- Buffer Volume (mL) (Buffer Vol (mL) = Number of Plates \* 5  $\frac{\text{mL}}{\text{Plate}}$ )
- uCi/uL ratio

#### 5.1.2 Formula

$$uCi = \frac{S.A. \; (Ci/mmol)*Buffer \; Vol \; (mL)*Assay \; Conc \; (nM)*2.5*1.44}{1000}$$
 
$$uL = uCi \; needed*\frac{uL}{uCi}(Ratio)$$

#### **5.1.3** Where

- 2.5 is the Dilution Factor, we add 50 uL of our hot ligand solution into each well, which then has a final volume of 125 uL. Therefore, we need to make our hotligand concentration  $\frac{125}{50} = 2.5$  times stronger to account for this.
- 1.44 is an overage percent; we take 44% more than what we need.
- 1000 is to handle the net results of converting units.

We calculate how much uCi is necessary to perform the assay, then we can determine what volume of ligand (uL) to remove from the vial to perform the assay at the specified concentration by multiplying the uCi needed by the uCi/uL ratio.