Containor	Operation		
Container	Category	Function-like Macros Prototype	Short Description
CCXLL	Create	<u>CCXLL</u> ccxll (TYPE) list;	Create a ccxll container list of type TYPE. This is implemented by a C struct to construct a list container.
		CCXLL ccxll_pckd (TYPE) list;	Create a packed ccxll container list of type TYPE. This is implemented by an aligned C struct to construct a list container.
		<u>CCXLL</u> ccxll_extd (TYPE, unsigned num, align) list;	Create a ccxll container list of type TYPE with <i>num</i> iterators. The container is packed when align is PACKED. Otherwise, set NORMAL for default.
	Initialize	void ccxll_init (CCXLL);	Initialize the ccxll container. CAUTION: Every container must be initialized right after its creation.
		<pre>void ccxll_iter_init (ITER, CCXLL);</pre>	Initialize the iterator for the ccxll container. CAUTION: Every iterator is implicitly initialized when the container it belongs to is initialized.
	Destroy	<pre>stat ccxll_free (CCXLL);</pre>	Deallocate all elements in the container manually. CAUTION: Every container should be destroyed before the program terminates.
	Access	TYPE& ccxll_front (CCXLL);	Return a reference to the first element. It's an undefined behavior if the container is empty.
		TYPE& ccxll_back (CCXLL);	Return a reference to the last element. It's an undefined behavior if the container is empty.
	Capacity	<pre>int ccxll_size (CCXLL);</pre>	Return the number of the elements in the container. Return 0 if the container is empty.
		<pre>int ccxll_empty (CCXLL);</pre>	Check whether the container is empty. Return 1 if the container is empty, and return 0 if it is not.
	Modifiers	<pre>stat ccxll_push_front (CCXLL, TYPE value);</pre>	Insert an element at the beginning. This makes a copy of value into the container.
		<pre>stat ccxll_push_back (CCXLL, TYPE value);</pre>	Insert an element at the end. This makes a copy of value into the container.
		<pre>stat ccxll_pop_front (CCXLL);</pre>	Remove the first element. There is nothing modified if the container is empty.
		<pre>stat ccxll_pop_back (CCXLL);</pre>	Remove the last element. There is nothing modified if the container is empty.
		<pre>stat ccxll_insert (ITER, TYPE value);</pre>	Insert an element at the position where the iterator points. This makes a copy of value into the container.
		<pre>stat ccxll_erase (ITER);</pre>	Erase an element at the position where the iterator points. There is nothing modified if the container is empty.
		<pre>stat ccxll_swap (CCXLL_A, CCXLL_B);</pre>	Swap two containers of the same type. It may cause unexpected errors if two containers are of different types.
		<pre>stat ccxll_resize (CCXLL, int num, TYPE value);</pre>	Resize the container to contain <i>num</i> elements. If the current size is smaller than <i>num</i> elements, then fills with value . Otherwise, it truncates.
	Operations	<pre>stat ccxll_clear (CCXLL);</pre>	Remove all elements in the container. This does not deallocate all elements in the container.
		<pre>stat ccxll_move_range (ITER_P, ITER_L, ITER_R);</pre>	Move the elements in the range [ITER_L, ITER_R) to position where ITER_P points. These three iterators should be affiliated to the same ccxll container.
		<pre>stat ccxll_merge[_extd] (CCXLL_A, CCXLL_B[, (*LEQ)()]);</pre>	Merge two sorted lists from CCXLL_B into CCXLL_A. Merge with the default comparator CCXLL_LEQ_COMPAR if _extd postfix is not specified.
		<pre>stat ccxll_sort[_extd] (CCXLL[, (*LEQ)()]);</pre>	Sort all elements in CCXLL. Sort with the default comparator CCXLL_LEQ_COMPAR if _extd postfix is not specified.
		<pre>stat ccxll_reverse_range (ITER_L, ITER_R);</pre>	Reverse the elements in the range [ITER_L, ITER_R]. This performs in constant time no matter how large the range is.
	Comparators	<pre>int</pre>	Compare values by passing and dereferencing two iterators for sorting algorithms. Return 1 iff the value pointed by ITER_L is not greater than the value pointed by ITER_R.
	Iterators	<pre>ITER ITER[_NTH] (CCXLL[, num]);</pre>	Return the <i>num</i> -th iterator of CCXLL. Return zeroth iterator if _NTH postfix is not specified.
		TYPE& DREF (ITER);	Return a reference to the element. It's an undefined behavior if the iterator is not invalid.
		TYPE& DREF_[PREV NEXT] (ITER);	Return a reference to the previous/next element. It's an undefined behavior if the iterator is not invalid.
		<pre>void ccxll_iter_copy (ITER_DST, ITER_SRC);</pre>	Copy the iterator from ITER_SRC to ITER_DST. It's not acceptable to assign the iterator by assignment operator.
		<pre>void ccxll_iter_[head tail] (ITER);</pre>	Set the iterator to the head/tail of the container. The head/tail of the container is the sentinel node pointing to the first/last element.
		<pre>void ccxll_iter_[begin end] (ITER);</pre>	Set the iterator to the first/last element usaully. Set the iterator to the tail/head if the container is empty.
		<pre>int ccxll_iter_at_[head tail] (ITER);</pre>	Check whether the iterator points to the head/tail of the container. Return 1 if it is true. Otherwise, return 0.
		<pre>int ccxll_iter_at_[begin end] (ITER);</pre>	Check whether the iterator points to the first/last element. Return 1 if it is true. Otherwise, return 0.
		<pre>void* ccxll_iter_[incr decr] (ITER);</pre>	Move the iterator forward/backward by one element. Return NULL iff the iterator doesn't point to any element before and after moving.
		<pre>stat ccxll_iter_advance (ITER, int diff);</pre>	Move the iterator by diff element(s). (regard forward as positive) The iterator will stop at the sentinel node if there is no element left to iterate over.
		<pre>stat ccxll_iter_distance (ITER_A, ITER_B, int *dist);</pre>	Return the distance between ITER_A and ITER_B through the pointer dist. Return 0 if the distance between them cannot be determined.
	Traversal -	<pre>loop CCXLL_[INCR DECR] (ITER) stat;</pre>	Traverse all elements forward/backword. This is implemented by a single for statement.
		<pre>loop CCXLL_[INCR DECR]_DREF (TYPE *pval, CCXLL) stat;</pre>	Traverse all elements forward/backword. This macro will not be activated if CCC_STRICT is defined.