# Generalised Extreme Value (GEV) distribution

### Parametrisation

The GEV distribution is defined through the cumulative distribution function

$$F(y; \eta, \tau, \xi) = \exp\left(-\left[1 + \xi\sqrt{\tau s}(y - \eta)\right]^{-1/\xi}\right)$$

for

$$1 + \xi \sqrt{\tau s}(y - \eta) > 0$$

and for a continuously response y where

 $\eta$ : is the linear predictor

 $\tau$ : is the "precision"

s: is a fixed scaling, s > 0.

## Link-function

The linear predictor is given in the parameterisation of the GEV distribution.

## Hyperparameters

The GEV-models has two hyperparameters. The "precision" is represented as

$$\theta_1 = \log \tau$$

and the prior is defined on  $\theta_1$ . The shape parameter  $\xi$  is represented as

$$\theta_2 = \xi$$

and the prior is defined on  $\theta_2$ . <sup>1</sup>

#### **Specification**

- family = gev
- Required arguments: y and s (keyword scale)
- The scaling  $\xi_s$  is given by the argument gev.scale.xi and is default set to 0.01.

The weights has default value 1.

<sup>&</sup>lt;sup>1</sup>Internally, the parameter  $\theta_2$  is scaled with a fixed scaling  $\xi_s$  (default 0.01), to improve the numerics as the natural "scale" of  $\xi$  is small. For this reason the  $\theta_2(=\xi)$  reported in result\$mode\$theta will appear as  $\theta_2/\xi_s$ . For the same reason, if you define the mode using control.mode = list(theta = ..., ...) then the element representing  $\theta_2$  should be given as  $\theta_2/\xi_s$ .

## Hyperparameter spesification and default values

doc The Generalized Extreme Value likelihood

```
hyper
```

```
theta1
         hyperid 76001
         name log precision
         short.name prec
         initial 4
         fixed FALSE
         prior loggamma
         param 1 5e-05
         to.theta function(x) log(x)
         from.theta function(x) exp(x)
    theta2
         hyperid 76002
         name gev parameter
         short.name gev
         initial 0
         fixed FALSE
         prior gaussian
         param 0 25
         to.theta function(x) x
         from.theta function(x) x
survival FALSE
discrete FALSE
link default identity
status experimental
pdf gev
```

### Example

In the following example, we estimate the parameters of the GEV distribution on some simulated data.

```
rgev = function(n=1, xi = 0, mu = 0.0, sd = 1.0) {
    u = runif(n)
    if (xi == 0) {
        x = -log(-log(u))
    } else {
        x = ((-log(u))^(-xi) - 1.0)/xi
    }
    return (x*sd + mu)
}
```

# Notes

None.