The Gamma-distribution

Parametrisation

The Gamma-distribution has the following density

$$\pi(y) = \frac{b^a}{\Gamma(a)} y^{a-1} \exp(-by), \qquad a > 0, \quad b > 0, \quad y > 0,$$

where $E(y) = \mu = a/b$ and $Var(y) = 1/\tau = a/b^2$, where τ is the precision and μ is the mean. We will use the following parameterisation for the precision

$$\tau = (s\phi)/\mu^2$$

where ϕ is the precision parameter (or $1/\phi$ is the dispersion parameter) and s > 0 is a fixed scaling, which gives this density

$$\pi(y) = \frac{1}{\Gamma(s\phi)} \left(\frac{(s\phi)}{\mu} \right)^{(s\phi)} y^{(s\phi)-1} \exp\left(-(s\phi) \frac{y}{\mu} \right)$$

Link-function

The linear predictor η is linked to the mean μ using a default log-link

$$\mu = \exp(\eta)$$

Hyperparameter

The hyperparameter is the precision parameter ϕ , which is represented as

$$\phi = \exp(\theta)$$

and the prior is defined on θ .

Specification

- family = gamma
- Required arguments: y and s (argument scale)

The scalings have default value 1.

Hyperparameter spesification and default values

doc The Gamma likelihood

hyper

theta

hyperid 58001 name precision parameter short.name prec initial 4.60517018598809 fixed FALSE prior loggamma

```
param 1 0.01
to.theta function(x) log(x)
from.theta function(x) exp(x)
survival FALSE
discrete FALSE
link default log
pdf gamma
```

Example

In the following example we estimate the parameters in a simulated example.

Notes

None.