

within

Karlsruhe UAC

Effective: February 26, 2025

1 General.

1.1 Purpose.

The purpose of these Local Operational Procedures and Orders is to define the coordination to be applied within Karlsruhe UAC when providing ATS to air traffic (IFR/VFR) on the VATSIM network

All information and procedures described in this Document shall not be used for real world purposes.

1.2 Validity.

The Local Operational Procedures and Orders laid out in this document become effective on February 26, 2025 and supersede previous local operational procedures established within Karlsruhe UAC from November 28, 2024 (AIRAC2412).

1.3 Revision control.

Revision	Date	Author	
1.0	30.11.2023	Hannes Altmann, Konstantin Eierhoff, Phil Hauf, Jannik Vogel	
1.1	22.02.2024	Hannes Altmann, Jannik Vogel	
1.2	03.10.2024	Jannik Vogel, Phil Hauf, Hannes Altmann	
1.3	28.11.2024	Jannik Vogel	
1.4	20.02.2025	David Dürr	

2 Areas of Responsibility and Sectorization.

2.1 Areas of Responsibility.

The lateral and vertical limits of the respective areas of responsibility are as follows:

2.1.1 Karlsruhe UAC.

Lateral limits: Rhein UIR as described in AIP Germany

Vertical limits: FL245 – FL660 (above Langen ACC)

FL285 – FL660 (above Bremen ACC) FL315 – FL660 (above München ACC)

2.2 Sectorization.

See here: vats.im/eduu

2.3 Delegation of the Responsibility for the Provision of ATS.

The area of responsibility of Karlsruhe UAC includes the delegated airspace as laid out in the Letters of Agreement with external units.

3 Procedures for Coordination.

3.1 Definitions.

A release is an authorization for the accepting ATS unit to climb, descend and/or turn (by no more than 45°) a specific aircraft before the transfer of control point. The transferring ATS unit remains responsible for separation within its Area of Responsibility unless otherwise agreed.

Wherever VATSIM callsigns are used to describe the terms of a certain procedure, this procedure is also applicable for all higher stations that take over the responsibilities of said station. E.g., procedures for an APP-stations are also applicable for the respective CTR station fulfilling the duties of said APP station.

3.2 Abbreviations.

Area Control Center		Knots	
Aerodrome	LOP	Local Operational Procedures	
Aerodrome of Departure	LoR	Line of Responsibility	
Aerodrome of Destination	NM	Nautical Mile	
Area of Responsibility	NVFR	Night Visual Flight Rules	
Approach Facility	RFL	Requested Flight Level	
Air Traffic Services	RIsd	Released	
Coordination Point	SSR	Secondary Surveillance	
Center/Enroute Facility	Radar	·	
Flight Information Region	TMA	Terminal Maneuvering Area	
Flight Information Service	UAC	Upper Area Control Center	
Flight Level	VFR	Visual Flight Rules	
Ground	WEF	With Effect From	
Global Nav Generator			
(gng.aero-nav.com)			
	Aerodrome Aerodrome of Departure Aerodrome of Destination Area of Responsibility Approach Facility Air Traffic Services Coordination Point Center/Enroute Facility Flight Information Region Flight Level Ground Global Nav Generator	Aerodrome LOP Aerodrome of Departure LoR Aerodrome of Destination NM Area of Responsibility NVFR Approach Facility RFL Air Traffic Services RIsd Coordination Point SSR Center/Enroute Facility Radar Flight Information Region TMA Flight Level VFR Ground WEF	

3.3 General Conditions.

Coordination of flights shall take place via the agreed coordination points (COP).

Coordinated flights shall be handed off via a valid COP. Any deviation shall be coordinated verbally, by text or by Euroscope inter-sector coordination.

Traffic shall be handed off at the levels, defined in the regulations below. If a specified level restriction cannot be met due to a lower RFL, traffic shall be handed off at RFL, if this does not cause a conflict with any other traffic. Otherwise, traffic shall be coordinated.

If a traffic situation is not covered herein or closely matching a covered one, individual coordination between the concerned sectors shall be made.

After Transfer of communications, traffic is NOT released for climb, descent or turns until Transfer of control or otherwise specified in the following local operational procedures and orders.

↓FLxxx / ↑FLxxx means "descending / climbing to a specified FL", without any further restriction. Any required crossing/speed restriction shall be added separately. At level means that the aircraft shall be in level flight on a published flight level and in accordance with east/ west odd/even policy.

FLxxxA means "climbing and above specified FL", FLxxxB means "descending and below specified FL".

3.4 Flights sorted by transferring sector.

3.4.1 EBG South

Targeted Flights	Transfer Condition	FROM sector	TO sector
Arr. EDDF, ETAR, ETOU, EDFZ, EDFE, EDGS, EDRK,	FL380 or	000101	000101
LKKV	below		
Arr. EDDS, EDSB, EDRY, EDRY, EDFM, EDQ*, EDDN, ETSI, ETSN	FL320		
Arr. LOWL	FL330 or below	ALP	СНІ
Arr. LOWW	FL370 or below		
Arr. LKCS	FL360 or below		
Arr. LOWW	FL370 or below	ALP	ISA
Arr. EDGS, EDFQ	FL320		
Arr. EDDK, EDKB, EDFH, EDDR, ELLX	FL340 or below	ALP	TGO
Dep. LOWI	FL340 or below		
Arr. LSMD, EDDS, EDSB, EDFM, ETAR, EDTD, EDTL, EDTM, EDTY, EDRY via KPT	FL320		
Arr. LIPZ, LIPH, LIPX, LIPO, LIPA	FL320		
Arr. LSZH	FL340 or below	СНІ	ALP
Arr. LIMP, LIPE, LIPK, LIME	FL350 or below		
Arr. LFST, LSZB, LSMA, LSMB, LSME, LSMF, LSML,	FL360 or		
LSMM, LSMO, LSMP, LSMS, LSMU, LFSB, LFGA, LFGB, LFSM	below		
Arr. LKPR, LKPD, LKKB, LKCV, LKHK, LKMH, LKVO	FL340 or below	СНІ	DON
Arr. EDDF, ETOU, EDFZ, EDFE, EDGS, EDRK via M726	FL360 or below		
Arr. ETAR, LKKV	FL340 or below		ISA
Arr. EDDF via Q863	FL360 or below	СНІ	104
Arr. EDDP, EDAC, EDDE, EDCD, EDFQ, EDVK via M726	FL360 or below		
Arr. LIPZ, LIPH, LIPX, LIPO, LIPA, LIPB, LZSZ, LSZA, LDZA, LDZA, LDRI, LJMB, LDPL, LDLO	FL360 or below	DON	CIII
Dep. LKPR	FL360 or below	DON	СНІ
Arr. EDDC	FL360 or below	DON	ED:
Dep. LOWL, LOWS	FL360 or below	DON	ERL
Arr. EDFH, ELLX, ETAD	FL320	DON	WUR
Arr. LIPZ, LIPH, LIPX, LIPO, LIPA, LIPB, LSZS, LSZA, LJLJ, LOWG, LOWK, LOXZ, LOWW, LDZA, LDRI, LJMB, LDPL, LDLO	FL350 or below	ISA	СНІ

Arr. EDDF, ETOU, EDFE, EDFZ, EDDP, EDAC, EDDE, EDCD, EDFQ, EDVK, LKPR, LKPD, LKKB, LKCV, LKHK, LKMH, LKVO	FL320	ISA	DON
Dep. EDDF via MIQ	FL350 or below		
Arr. EDDK, EDKB, EDFH, EDDR, ELLC	FL340 or below	ISA	TGO
Arr. EDGS, EDFQ	FL320	IJA	130

3.4.2 EBG East

Targeted flights	Condition	FROM Sector	TO sector
Arr. LOWS, LOWI, LOWL	FL320		
Arr. LOWW	FL370 or below	ERL	DON
Arr. EDDK, EDKB, EDKZ, EDLA, EDLE, EDLM, EDLD, EDLI, EDLP, EDLW	PILAM at FL320	ERL	FUL
Arr. EDDV, EDVE, ETNW	FL360 or below		. 02
Arr. EDDR, EDFH, ELLX, EDSB, EDRZ, ETAD	FL320		
Arr. EBLG, EBZW, EHBK, LFLJ, LFSN	FL360 or below	ERL	WUR
Arr. EDTM, EDTD	FL340 or below		
Arr. EDDR, EDDS, EDFM, EDFV, EDJA, EDMS, EDRY, EDTL, EDTY, ETAR, ETIN, ETHN, ETOR, LKKV	FL360 or below		
Arr. EDDF, EDFE, EDFQ, EDFZ, ETOU (except via DIDGI and TOPDI)	FL340 or below	HVL	SAL
Arr. LKPR, LKPD, LKKB, LKCV, LKHK, LKMH, LKVO	FL350 or below		
Arr. LKPR, LKPD, LKKB, LKCV, LKHK, LKMH, LKVO, LKPM	FL350 or below		
Arr. LKCS	FL370 or below	HVL	SPE
Arr. EDDP via SUVAL	FL290	OSE	HVL
Arr. LOWS, LOWL	FL370 or below		
Arr. LOWI	FL350 or below	SAL	ERL
Arr. EDSB, EDTM	FL360 or below		
Arr. LKPR, LKPD, LKKB, LKCV, LKHK, LKMH, LKVO, LKCS	FL320	SAL	SPE
Arr. EDDV, EDLP, EDLI, EDVK, ETNW	FL360 or below	SPE	HVL
Arr. EDDW via KOSIX-L986-MAG	FL360 or below	Jr E	IIVL
Arr. EDDF, EDFE, EDFQ, EDFZ, ETOU via TADUV	FL360 or below		
Arr. EDDF, EDFE, EDFQ, EDFZ, ETOU on DCT SULED- ROBEL	FL360 or below	SPE	SAL
Arr. EDDF via SODRO-SULUS	FL340 or below	SPE	SAL
Arr. EDDM, EDMA, EDMO	FL350 or below		

3.4.3 EBG Central

Targeted flights	Condition	FROM sector	TO sector
Arr. EDDP, EDAC, EDBC, EDBM	FL350 or below		
Arr. EDDV, EDVE, ETNW	FL330 or below	FFM	FUL
Arr. EBBR, EBMB, EBAW, EBCV, EBCI, EHEH, EHWO, EHGR, EHVK	FL320 or below	FFM	NTM
Arr. EBLG, EBZW, EHBK, LFJL, LFSN	FL300 or below		
Arr. EDTF, EDTD, LSZH, LFSB, LSZR, LSMD, EDNY, EDTM, EDJA Dep. EDDL, EDDG, EDDK, EDGS, EDKB, EDKL,	FL350 or below		
EDLA, EDLE, EDLM, EDLN, EDLP, EDLW, ETNG, ETNN		FFM	SLN
Arr. EDTL, EDTO	FL310 or below		
Arr. EDMA, EDMO, ETSI, ETSL, EDJA, ETSN	FL270 or below		
Arr. EDDM			
Dep. EDDL, EDDG, EDDK, EDGS, EDKB, EDKL, EDLA, EDLE, EDLM, EDLN, EDLP, EDLW, ETNG, ETNN	FL350 or below	FFM	WUR
Arr. LKKV, EDMS	FL290 or below		
Arr. EDDN, EDQC, EDQD, EDQK, EDQM, EDQT, EDTY, EDQA	FL250		
Arr. EDTF, EDTD, LSZH, LFSB, LSZR, LSMD, EDNY, EDTM, EDJA	FL390 or below		
Dep. EDDV, EDVE	FL350 or below	FUL	FFM
Arr. EDSB, LFGA, LFST	FL310 or below		
Arr. LKPR, LKKB, LKVO, LKCV, LKHK, LKMH, LKPD, LKCS	FL370 or below	FUL	ERL
Arr. EDDB	FL360 or below	FUL	SAL
Arr. EDDS, EDSB, EDTY, EDTL, EDTM, EDMA, EDMO, ETSI, ETSL, ETSN, EDJA	(Even and Odd) FL250	FUL	WUR
Arr. LKPR, LKKB, LKVO, LKCV, LKHK, LKMH, LKPD, LKCS, EDDC	FL370 or below	WUR	ERL
Arr. ETNG, EBLG, EBZW, EHBK, LFJL, LFSN	FL340 or below	MATERIAL	
Arr. EBBR, EBMB, EBAW, EBCV, EBCI, EHEH, EHWO, EHGR, EHVK	FL380 or below	WUR	FFM
Arr. EDLA, EDLW, EDLE, EDLM, EDLD, EDKZ, EDLP, EDLI, EDVK	FL280 or below		
Arr. EDDP, EDAC	FL330 or below	WUR	FUL
Arr. EDDV, EDVE, ETNW	FL360 or below		
Arr. LOWL	FL370 or below	WUR	ISA
Arr. LSZH, LSZR, LSMD, EDNY, EDTO, EDTF, EDTL, LFJL, LFSB, LFST, LFGA	FL320 or below	WUR	TGO
Arr. EDTM, EDTD	FL280 or below		

3.4.4 EBG West

Targeted flights	Condition	FROM sector	TO sector
Arr. EDDN, EDDE, EDTY, EDQT, EDQC, EDQD,	FL290 or	00000	
EDQM, EDQA	below		
Arr. EDMA, EDMO, ETSI, EDJA, ETSN, ETSL	FL310 or		
7 25, 25, 210., 210., 210.	below		
Arr. LKKV, EDMS	FL330 or	NTM	FFM
7 2	below		
Arr. EDDV, EDVE, ETNW	FL350 or		
7.111 2551, 2512, 211111	below		
Arr. EDDM	FL390 or		
	below		
Arr. EDTF, EDTD, EDJA, LSZH, LFSB, LSZR, LSMD,	FL330 or		
EDNY, EDTM	below	NTM	SLN
Arr. EDTL, EDTO	FL310 or	INTIVI	SLIN
AII. LDTL, LDTO	below		
Arr. EBBR, EBMB, EBAW, EBCV, EBCI, EBLG,	FL320 or		
EBZW, EHBK, EHBD, LFSN	below	SLN	NTM
Arr. EHEH, EHWO, EHGR, EHVK	FL340 or	SLN	IN I IVI
AII. EHEH, EHWO, EHGK, EHVK	below		
A LOWI LC7C LC7A LC7L LIDD	FL350 or		
Arr. LOWI, LSZS, LSZA, LSZL, LIPB	below	CLN	TCO
A FDDM	FL310 or	SLN	TGO
Arr. EDDM	below		
A EDDM	FL330 or	CLN	WILD
Arr. EDDM	below	SLN	WUR
A LOWIC	FL350 or		
Arr. LOWS	below	TGO	ALD
A LIMO LIME LIME LIDZ LIDU LIDV LIDO LIDA	FL370 or	FL370 or	ALP
Arr. LIMC, LIML, LIME, LIPZ, LIPH, LIPX, LIPO, LIPA	below		
A D.7.4 D.D. 1840 1.00 D.D. 1.01 0	FL370 or	T00	10.4
Arr. LDZA, LDRI, LJMB, LIPQ, LDPL, LDLO	below	TGO	ISA
Arr. LSGC, LSMA, LSME, LSMP, LSZB, LSZC, LSZG, LSZM	FL250		
A Wid in 1 0 4 0 4 1 0 0 ± 1 0 1 ± 1 0 7 ±	FL270 or		
Arr. Within LSAS except LSG*, LSM*, LSZ*	below		
	FL280 or		
Arr. EDDK, EDKB	below		
A FILW	FL300 or	TGO	SLN
Arr. ELLX	below		
Arr. LSGG, LSGS, LSZA, LSZL, LSZS, LFLB, LFLI,	FL310 or		
LFLJ, LFLP	below	_	
•	FL330 or		
Arr. LIMC	below		
Arr. EDLA, EDLW, EDLE, EDLM, EDLD, EDKZ, EDLP,			
EDLI, EDVK	FL340 or below	TGO	WUR
·			
Dep. LSZH			

4 Special Procedures.

4.1 Internal Tactical Directs.

Following tactical directs can generally be cleared provided that sector sequence and a distance to sector boundaries of 2,5 NM or greater is maintained.

4.1.1 EBG South

Available DCT	FROM Sector	TO Sector
INPUL, LASMI, AGNAV, RUDNO, TIVDA, BADVI, MAH, MEBEK, KONIN (1)	ALP	СНІ
AGNAV, RUDNO, TIVDA, UMDAS, ETASA, PETIX, HAREM, ASPAT (1)	ALP	ISA
HAREM, UMDAS, ETASA, TEDGO, BANIM, IBGES, SUNEG	ALP	TGO
BERAS, LIZUM, LIKDA, OLPIX, KPT (1)	СНІ	ALP
AGNAV, RUDNO, TIVDA (Change of sector sequence allowed) (1)	СНІ	DON
MAH, AGNAV, RUDNO, TIVDA, LASMI, UMDAS, ETASA, ASPAT, BABEG, SUNEG (1)	СНІ	ISA
LARET, MAPOX, MASEK, ABGUS, ZUCKA, ESAMA, GASKA and all waypoints withing EBG East	DON	ERL
KUMOM, EBEDA	DON	СНІ
LOHRE, COSJE, PETIX, ESAMA	DON	WUR
OTT, EBEDA, GOMIG, VAVOR, LATLO, RADIZ	ISA	СНІ
AGNAV, RUDNO, TIVDA, PETIX, ASPAT (Change of sector sequence allowed) (1)	ISA	DON
HAREM, UMDAS, ETASA, SUNEG	ISA	TGO

⁽¹⁾ Transfers to EDMM shall not be cleared further than respective COP.

4.1.2 EBG East

Available DCT	FROM Sector	TO Sector
DEXIT, ALUTU, SIMBA, LAMSI, RUDNO, RUDAP, DOSEL (except Arr. LOWI, LOWS, LOWL)	ERL	DON
MAPOX, MASEK, ARNIX, AMETU, GASKA	ERL	FUL
Overflights: All waypoints within WUR ESAMA Arrivals via COSJE: COSJE	ERL	WUR
 Overflights: all waypoints or maximum last UAC waypoint and DKB Arr. EKCH: MONAK Arr. EDDH: BUMIL, ABGUS Arr. EDDW: GURLO Arr. LKPR: HDO, LALUK Arr. EDDM: SODRO Arr. EPWR: LASIS Arr. EPPO: SUBIX 	Within I	EBG East

4.1.3 EBG Central

Available DCT	FROM Sector	TO Sector
MASEK, FEDZA, ROBEL, TAMEB	FFM	FUL
BUB, UMUPU, ADKUV, RUDUS	FFM	NTM
GIGET	FFM	SLN
 Overflights: all waypoints within WUR and ERL sector Arr. EDDM: ELMOX Arr. LKPR: TONSU OKG and ENITA 	FFM	WUR
TIVUN	FUL	FFM
OKG, TONSU	FUL	ERL
SUBIX, LASTO, TAMEB	FUL	SAL
OSBIT	FUL	WUR
 Overflights: All waypoints within ERL sector Arr. LKPR: OKG, RUDAP, ENITA, TONSU 	WUR	ERL
BUB, ESAMA, BOMBI, ADKUV, ARPEG (north of LOHRE)	WUR	FFM
 Overflights: All waypoints within FUL sector (except Arr. EDDV): MADOR, NORTA 	WUR	FUL
AKANU, XERUM (when entering ISA between GEBNO and DINKU)	WUR	ISA
TEDGO	WUR	TGO

4.1.4 EBG West

Available DCT	FROM Sector	TO Sector
MASEK, TAMEB, FEDZA, ROBEL, TESGA	NTM	FFM
MADEB, OTRES, TIRUL, IRBIR, ELMEM, MOMUK	TGO	ALP
HAREM, TIKNI	TGO	WUR
 Overflights: All waypoints withing EBG West TRA, LUTIX, ROTOS, COA, DENUT, BUB, IDOSA, LIRSU Arr. LSZH, LSAZ, EDNY, LSMD: LAMGO Arr. EHEH: ROLIS Arr. EB**: IDOVI Arr. EDDK: UMDAS (north of KOVAN) Arr. ELLX: IBGES Arr. LFSB: KRH 	Within EB	G West

4.2 Enroute level allocations.

Generally, flights shall be handed off in accordance with Even-Odd-Rule, except otherwise specified in the table below or the procedures laid down in section 3.4 of this LOP.

FROM Sector	TO Sector	Allocation	Exceptions and Remarks
ALP	СНІ		Traffic on M726 (even)
ALP	ISA		
СНІ	ALP	Even/Odd	
СНІ	DON		
DON	СНІ		Departures LKAA FIR (even)
DON	ERL	Even	Flights from ISA via SAL (even/odd)
ISA	DON	Odd	 Flights via ERL (even/odd) Flights via AGNAV/TIVDA (even/odd) Flights via WUR (even)
Arrivals within	n EBG East	Even/Odd	If flight starts its initial descent in EBG East
ERL	DON	Odd	
ERL	SAL	Even	Flights via SPE (odd)Flights via EPWW (even/odd)
ERL	WUR	Even	Flights via TGO (even/odd)
HVL	OSE	Even	Flights via EPWW (odd)Flights via ESMM (even/odd)
HVL	SAL	Odd	Flights via WUR sector (even/odd) Flights via FUL sector (even/odd)
HVL	SPE	Odd	Flights via MAREM (even/odd) Flights via ERL sector (even/odd)
OSE	HVL	Odd	 Flights via EDYY (even) Flights via MAREM (even/odd) Flights via WUR sector (even/odd)
SAL	ERL	Odd	Flights via TGO and WUR (even/odd)Flights via WUR and FFM (even)
SAL	HVL	Even	Flights via EPWW (odd) Flights via ESMM (even/odd)
SAL	SPE	Odd	-
SPE	HVL	Even	Flights via EPWW (odd)Flights via ESMM (even/odd)
SPE	SAL	Even	Flights via ERL (even/odd)
FFM	SLN	Odd	
FUL	SAL	Odd	Flights via ROBEL/TAMEB (even/odd)
WUR	FUL	Even	Flights via SAL (even/odd)
WUR	TGO	Even/Odd	
TGO	WUR	Even	

5 Transfer of Control and Transfer of Communication.

5.1 Transfer of Control.

Transfer of Control shall take place at the AoR boundary.

If the downstream sector in EuroScope is set to >.break<, the procedure 5.4 is suspended and transfer of communication can only take place after the downstream sector has assumed the flight via the appropriate function of the radar client.

If it becomes necessary to reduce or suspend transfers, a 5-minute prior notification is required.

When transfers are suspended, the hand-off procedure (5.4) is suspended.

5.2 Silent transfer of control.

Radar transfer without coordination between aircraft proceeding in the same direction may be carried out provided that the minimum distance between the aircraft is never less than 10 NM within the time of transfer until 20 NM beyond the common sector boundary.

5.3 Transfer of Communications.

Transfer of Communications shall take place no later than Transfer of Control.

5.4 Hand-Off procedure.

Unless otherwise agreed between stations online, the following hand-off procedure shall apply:

- The upstream sector sends the aircraft to the frequency of the downstream sector by voice or text.
- 2. The upstream sector initiates a transfer via the appropriate function of the radar client.
- 3. Upon initial call the downstream sector assumes the flight via the appropriate function of the radar client.