

CAMERA FUNDAMENTALS

Master Your Camera in a Weekend

The Exposure Triangle & Manual Mode, Made Simple

Story Mode Guy

storymodeguy.com

Reader's Edition · 2026

\$27 value

What's Inside

The Exposure Triangle & Manual Mode, Made Simple. Written for new DSLR & mirrorless owners intimidated by the mode dial.

- 01** **Get Off Auto This Weekend**

- 02** **Meet the Three Controls**

- 03** **Aperture & Depth of Field**

- 04** **Shutter Speed & Motion**

- 05** **ISO & Image Quality**

- 06** **Reading the Meter & Histogram**

- 07** **Priority Modes — Your Training Wheels**

- 08** **Full Manual, Step by Step**

- 09** **12 Real-World Settings Recipes**

- 10** **Practice Drills & Next Steps**

INTRODUCTION

Get Off Auto This Weekend

That green AUTO mode is the training wheels you were supposed to take off. This weekend, you finally do. By Sunday night you will understand exactly what your camera is doing when it makes a picture — and you will be the one telling it what to do, on purpose, every single time.

Here is the truth nobody tells nervous beginners: the mode dial is not hard. It only looks hard because three little controls all affect one thing — brightness — while each *also* quietly shapes your photo in its own way. Once you see how those three fit together, the whole camera clicks into place. It stops being a machine that guesses and becomes an instrument you play.

"Exposure" just means **how much light lands on your sensor**. Too much and the photo is a blown-out white mess. Too little and it's a muddy, dark disappointment. Auto mode tries to hit the middle for you — and it usually gets the brightness roughly right. But it does that by making creative decisions *for* you: it decides whether your background is blurry or sharp, whether motion is frozen or streaked, whether your photo is clean or grainy. Those aren't brightness decisions. Those are the decisions that separate a snapshot from a photograph.

THE WHOLE GUIDE IN ONE SENTENCE

Three controls — aperture, shutter speed, and ISO — set your brightness together, and each one also decides one creative thing; learn what that second job is and you own your camera.

How to use this guide

Read it in order the first time — each chapter builds on the last. Chapters 2 through 5 teach the three controls one at a time. Chapter 6 teaches you to read the camera's built-in light meter so you know when your exposure is right. Chapter 7 hands you "priority" modes, the honest halfway house where most photographers happily live for months. Chapter 8 gives you a repeatable full-manual routine. Then Chapter 9 is twelve ready-to-shoot recipes, and Chapter 10 is your weekend practice plan.



Works with your camera

Every idea here is true on any DSLR or mirrorless camera, Canon, Nikon, Sony, Fujifilm, or otherwise. Where a control has a different name by brand, we give both. You already own everything you need. The only upgrade this weekend is you.

CHAPTER 1

Meet the Three Controls

Everything in this guide comes back to three settings. They are the entire game. Master these and there is nothing on the mode dial left to fear.

Picture your sensor as a small dark room, and the photo as how much daylight you let flood in. You have exactly three ways to control that flood.

Aperture

The **size of the window** in the lens. A bigger opening lets in more light at once. Measured in f-numbers like f/2.8 or f/8.

Shutter Speed

How **long the curtain stays open**. A longer time lets in more light. Measured in seconds and fractions, like 1/200s.

ISO

How much the camera **amplifies the signal** after the light arrives. Higher ISO brightens a dark scene — with a cost. Measured 100, 400, 1600...

The second job — this is the whole point

If all three did was control brightness, you could pick any combination and be done. But each control has a *side effect*, and that side effect is where photography actually lives.

Control	Its job (brightness)	What it ALSO changes
Aperture	Wider = brighter	Depth of field — how much is in focus front-to-back
Shutter speed	Slower = brighter	Motion — frozen crisp or streaked with blur
ISO	Higher = brighter	Noise — clean image or grainy speckle

Read that table twice. It is the exposure triangle, and it is genuinely all there is. When you change one control for its *brightness*, you inherit its *side effect* whether you wanted it or not. Shooting a waterfall silky-smooth? That's a slow shutter — a brightness choice with a motion side effect. A portrait with a dreamy blurred background? That's a wide aperture — a brightness choice with a depth-of-field side effect.

REMEMBER

You are never just setting brightness. Every exposure choice is also a creative choice — and you get to make it on purpose.

Stops — the camera's unit of "twice as much"

You'll hear the word **stop** constantly. A stop is simply a doubling or halving of light. Open the aperture one stop and twice as much light comes in; slow the shutter one stop, same thing; raise ISO one stop, the image gets twice as bright. This matters because the three controls speak the same language. If you make the shutter one stop darker to freeze motion, you can make the aperture one stop brighter to pay it back — and your total exposure stays the same. That trade is the heartbeat of manual photography.



The see-saw mental model

Think of exposure as a see-saw that must stay level. Take a stop of light away here, add a stop back there, and the brightness holds while the *look* changes. Once this clicks, manual mode stops being math and starts being choices.

CHAPTER 2

Aperture & Depth of Field

Aperture is the control that makes photos look "professional," because it governs that creamy, blurred background everyone wants. It is also the single most confusing setting for beginners, thanks to one backwards little quirk. Let's kill that confusion right now.

Why a smaller number means a bigger opening

Aperture is written as an f-number: f/1.8, f/4, f/11. The backwards part is that **a smaller number is a bigger opening**. f/1.8 is a wide, gaping window that floods the sensor with light. f/16 is a tiny pinhole. It feels wrong until you learn why: the f-number is a *fraction*. It's the lens focal length divided by the opening's diameter. Just like $\frac{1}{2}$ of a pizza is more than $\frac{1}{16}$ of a pizza, f/2 is a bigger hole than f/16.



Say it once, remember forever

Small f-number = big opening = more light = blurrier background. Big f-number = small opening = less light = more in focus. Tape that to your lens if you must.

Depth of field — the creative payoff

Depth of field is how much of your scene is sharp from front to back. A **shallow** depth of field (wide aperture, low f-number) keeps a thin slice in focus and melts everything else into blur — perfect for making a subject pop. A **deep** depth of field (narrow aperture, high f-number) keeps everything sharp from the flowers at your feet to the mountains behind — perfect for landscapes.

😊 Wide open (f/1.8-f/4)

Blurry, buttery backgrounds. Subject leaps off the frame. Great for portraits, food, single objects, low light. Only a thin plane is sharp, so nail your focus on the eye.



Stopped down (f/8-f/16)

Front-to-back sharpness. Everything crisp. Great for landscapes, architecture, group shots where every face must be sharp. Needs more light or a slower shutter.

The sharpness sweet spot

Here's a secret that saves beginners endless frustration: lenses are **not sharpest wide open**. Nearly every lens hits peak sharpness two or three stops down from its maximum — usually around **f/5.6 to f/8**. Wide open at f/1.8 you trade a little

edge sharpness for that gorgeous blur. And past $f/16$, a physics effect called diffraction actually *softens* the whole frame again. So for critical sharpness when you don't need extreme blur or extreme depth, live around $f/5.6$ – $f/8$.

Wide apertures are unforgiving

At $f/1.8$ the sharp zone can be thinner than a person's face. Focus on the near eye and even the far eye may go soft. Beginners often blame the lens when the real fix is: focus more carefully, or stop down to $f/2.8$ – $f/4$ for a little breathing room.

Portrait — subject pops off a blurred background

STARTING POINT

Aperture $f/2.8$

Shutter $1/250s$

ISO 200

Outdoors in good light. Focus on the near eye. Want more blur? Open to $f/1.8$ and step closer. Want both eyes and the ears sharp? Stop to $f/4$.

Landscape — sharp from foreground to horizon

STARTING POINT

Aperture $f/11$

Shutter $1/125s$

ISO 100

On a tripod you can slow the shutter and drop ISO for maximum quality. Focus about a third of the way into the scene for the deepest sharpness.

Three things deepen background blur

Depth of field isn't only about aperture. You get more background blur by (1) opening the aperture, (2) getting physically closer to your subject, and (3) using a longer focal length. Stack all three — 85mm, up close, at $f/2.8$ — and even a modest lens produces stunning separation.

CHAPTER 3

Shutter Speed & Motion

Shutter speed controls time. It's how long the sensor is exposed to light — and because the world moves during that sliver of time, shutter speed is the control that either **freezes** the action or lets it **blur**. This is the most intuitive of the three, and the most fun to play with.

Reading the numbers

Shutter speeds are mostly fractions of a second: 1/1000s is very fast (a thousandth of a second), 1/30s is slow, and a full 1" or longer is very slow. Faster shutter = less light in = frozen motion. Slower shutter = more light in = motion blur. On the dial, each doubling — 1/125 to 1/250 — is one stop of light.



Fast shutter (1/500s+)

Freezes a splash mid-air, a running dog, a jumping kid. Crisp and sharp. Costs light, so you may need a wider aperture or higher ISO to compensate.



Slow shutter (1/15s and below)

Silky waterfalls, light-trail streaks, that sense of motion. Requires a tripod or the whole frame blurs from your hands shaking.

The handholding reciprocal rule

Even a still subject goes blurry if *you* move during the shot. The safe minimum handheld shutter speed is **1 over your focal length**. At 50mm, use 1/50s or faster. At 200mm, use 1/200s or faster, because a long lens magnifies your hand-shake just as it magnifies the subject.



Crop-sensor correction

Most beginner cameras have a crop sensor. Multiply your focal length by the crop factor first — 1.5× for most brands, 1.6× for Canon. A 50mm lens then behaves like 75mm, so aim for 1/80s, not 1/50s. When unsure, round up to the next faster speed.

Shutter speeds by subject

FIELD-TESTED

Still person → **1/125s**

Walking → **1/250s**

Kids/pets playing → **1/500s**

Sports/running → **1/1000s**

Birds/cars → **1/2000s**

Motion *across* the frame needs a faster shutter than motion *toward* you. A cyclist crossing left-to-right smears far more than one riding straight at you.

When slow is the point

Sometimes blur is the goal. A waterfall at 1/2s turns to silk. City traffic at 4 seconds becomes ribbons of red and white light. A slow shutter while you *pan* the camera with a moving subject keeps the subject sharp and streaks the background into speed-lines. All of these need the camera locked down on a tripod, because at those speeds your heartbeat alone will smear the shot.

Silky waterfall

TRIPOD REQUIRED

Aperture **f/16**

Shutter **1/2s - 2s**

ISO **100**

Narrow aperture and low ISO help you reach a slow shutter in daylight. In bright sun you may still need a neutral-density filter — think of it as sunglasses for the lens.



Turn stabilization off on a tripod

In-body (IBIS) or in-lens stabilization is magic for handheld work — worth 2–5 stops. But on a tripod it can hunt for movement that isn't there and *add* tiny blur. When the camera is locked down, switch stabilization off.

CHAPTER 4

ISO & Image Quality

ISO is the third leg of the triangle, and it's the one to reach for *last*. Aperture and shutter change how much real light hits the sensor. ISO doesn't gather any new light — it **amplifies** the signal you already captured. Turn up the amplifier and the picture brightens, but the graininess, called *noise*, comes up with it.

The volume-knob analogy

Think of ISO like the volume on a cheap speaker. At low volume the music is clean. Crank it and you hear hiss under the song. ISO is the same: at base ISO the image is clean; push it high and digital "hiss" — speckly noise — creeps into shadows and smooth areas like skies.



Base ISO is your friend

Every sensor has a native **base ISO**, usually 100 (sometimes 64 or 200), where it produces the cleanest, highest-quality image with the widest range of tones. Use it whenever there's enough light. Only leave it when you must.

How high can you push it?

This depends on your camera and, honestly, on how big you'll display the photo. Noise that's obvious at 100% on your monitor often vanishes in a print or an Instagram post. Modern cameras are shockingly good. Here's a realistic starting map — test your own body to find its personal limit.

ISO	Typical scene	Quality
100–200	Bright sun, tripod work, studio	Cleanest possible
400–800	Overcast, open shade, bright indoors	Excellent, noise invisible
1600–3200	Dim indoors, evening, events	Good; slight grain in shadows
6400	Dark rooms, concerts, night street	Usable; noticeable but fine
12800+	Near-dark, last resort	Grainy; a sharp grainy shot still beats a blurry clean one

THE GOLDEN RULE OF ISO

A grainy sharp photo is a keeper. A clean blurry one is trash. Never let fear of noise force you into a shutter speed too slow to hold. Raise the ISO and get the shot.

Auto ISO with a ceiling — the smart default

Here's a setting that changes lives: **Auto ISO with a maximum limit**. You tell the camera "use as low an ISO as you can, but never go above 6400." Now you're free to pick aperture and shutter for their creative effect, and the camera fills in exactly enough ISO to make the exposure work — without ever running away into ugly territory. Most cameras also let you set a *minimum shutter speed* for Auto ISO, so it won't dip below, say, 1/125s and reintroduce blur. This one setting gives you manual-level control with a safety net.



Set your ceiling once

Dig into your menu, find Auto ISO, and set a maximum you're comfortable with — 6400 is a sane starting point for most recent cameras. Set the minimum shutter to 1/125s. Now Auto ISO is a teammate, not a wildcard.

CHAPTER 5

Reading the Meter & Histogram

You now know the three controls. But how do you know if your exposure is actually *right*? Your camera has two tools that tell you the truth: the light meter while you shoot, and the histogram after. Learn to read both and you'll never guess at brightness again.

The exposure meter

Half-press the shutter and look for a little scale at the bottom of the viewfinder or screen, marked **-2 ... -1 ... 0 ... +1 ... +2**. A marker slides along it. The camera is telling you: at your current settings, it thinks the shot will be too dark (marker toward -), too bright (toward +), or just right (at 0). In manual mode, your job is to adjust aperture, shutter, or ISO until that marker sits where you want it — usually at 0 to start.



Zero isn't sacred

The meter aims for an "average" brightness, which is only a suggestion. For a bright, airy photo you might set it to +1. For a moody, dark one, -1. The meter is a starting reference, not a boss.

Metering modes — how the camera measures

Mode	What it reads	Use when
Evaluative / Matrix	The whole frame, intelligently	Your everyday default — reliable most of the time
Center-weighted	Mostly the middle	Subject is centered; portraits
Spot	One tiny point you choose	Tricky backlight; measuring a specific face or highlight

Why the camera gets fooled

The meter assumes the world averages out to a middle gray. Point it at a snowy field and it thinks "far too bright!" and darkens everything — turning white snow dingy gray. Point it at a black cat and it brightens the shot until the cat is muddy gray. Backlight fools it the same way: a bright window behind your subject makes the camera darken the whole frame, leaving your subject a silhouette.

Exposure compensation — the fix

When the camera guesses wrong, you override it with **exposure compensation** (the +/- button). Snowy scene coming out gray? Dial in +1 or +2 and it brightens back to white. Subject too dark against a bright window? Add +1 to +2. This works in Auto ISO manual and in the priority modes of the next chapter. Remember it as: *white scene, add light; dark scene, subtract*.



Snow and beaches lie to your meter

Bright, evenly-lit scenes are the classic trap. Left alone, the camera underexposes them into a dull gray. Always add +1 to +2 stops of compensation for snow, sand, or a white wall behind your subject.

The histogram — the real truth

Your screen brightness lies; it looks different in sunlight than in a dark room. The **histogram** doesn't lie. It's a simple graph of your photo's tones, dark on the left, bright on the right, with the count of pixels at each brightness. Read it like a landscape.



A hill bunched hard against the **left** wall = crushed shadows, detail lost in the dark. Add light.



A hill spiking against the **right** wall = blown highlights, detail lost in the white. Remove light.



A nicely spread hump that doesn't slam either wall = a healthy exposure with detail everywhere.



Expose to the right — gently

Digital sensors record more detail in the brighter tones, so a slightly bright exposure (the histogram pushed toward the right without touching the wall) captures the cleanest files with the least noise. You then pull it back down in editing. Push right — but never so far that highlights clip off the right edge, because that detail is gone forever.

The back-of-camera image tells you what the photo looks like. The histogram tells you what the photo is.

CHAPTER 6

Priority Modes — Your Training Wheels

Here's permission you didn't know you needed: **you do not have to start in full manual**. Between Auto and Manual sit two brilliant "semi-automatic" modes that give you creative control over the one thing that matters for your scene, while the camera handles the rest. Most working photographers spend the majority of their time here. There is nothing to be ashamed of — these modes are faster and smarter for most situations.

Aperture Priority (A / Av)

You set the **aperture** and the ISO; the camera picks the matching shutter speed. This is the most-used mode in all of photography, because for most photos the depth of field is the creative decision you care about. Choosing portraits with a blurry background? Set f/2.8 and let the camera sort the shutter. Want a landscape sharp throughout? Set f/11 and the camera handles the rest.



Aperture Priority is the default answer

When you don't know which mode to use, use Aperture Priority. Set ISO (or Auto ISO with a ceiling), choose your aperture for the look you want, and shoot. Glance at the shutter speed the camera picks — if it's too slow to handhold, open up or raise ISO.

Shutter Priority (S / Tv)

You set the **shutter speed** and ISO; the camera picks the aperture. Reach for this whenever *motion* is the point — freezing your kid's soccer game at 1/1000s, or blurring a waterfall at 1/2s. You guarantee the motion look you want and the camera figures out the brightness.

A Reach for Aperture Priority when...

- Depth of field is the priority
- Portraits, landscapes, food, products
- Light is steady, subject isn't racing
- Honestly — most of the time

S Reach for Shutter Priority when...

- Motion is the priority
- Sports, kids, pets, wildlife
- Intentional motion blur
- You must freeze or streak the action

Compensation is your steering wheel

In both priority modes the camera sets brightness for you — so when it guesses wrong (snow, backlight, a dark subject), you correct with **exposure compensation**, exactly as in the last chapter. Priority mode plus the +/- dial is a genuinely complete way to shoot. Many pros never do more than this.

PERMISSION GRANTED

Living in Aperture or Shutter Priority is not cheating. It is choosing the one creative variable that matters and letting a very smart machine handle the arithmetic. Full manual is a tool, not a moral test.

CHAPTER 7

Full Manual, Step by Step

Now the moment you bought this guide for. Full Manual (M on the dial) means *you* set all three controls. It sounds daunting; it's actually a calm, repeatable routine. Use it when the light is tricky or unchanging — studio work, concerts, night scenes, panoramas, anything where you want every frame to match exactly. Here is the routine that works every time.

1 **Decide what the photo is *about*.**

Motion, or depth of field? That answer tells you which control to lock first. A running dog is about motion; a portrait is about depth. This is the same choice the priority modes made for you — now you make it consciously.

2 **Set the priority control first.**

Motion shot → set your shutter speed (say 1/1000s to freeze it). Depth shot → set your aperture (say f/2.8 for a blurred background). Lock in the one that matters.

3 **Set ISO for the light.**

Bright outdoors → ISO 100. Indoors → ISO 800–1600. Dark → 3200+. Or use Auto ISO with a ceiling and let it float. This is your rough brightness knob.

4 **Set the third control to balance the meter.**

Adjust the remaining control (aperture or shutter) until the exposure meter sits near 0 — or where you want it for a brighter or darker mood. This is where the see-saw balances.

5 **Take the shot and chimp the histogram.**

"Chimping" is checking the back screen after a shot. Glance at the histogram: bunched left, add light; slammed right, remove light. Trust the graph, not how bright the screen looks.

6 **Adjust one stop and reshoot if needed.**

Too dark? Slow the shutter a stop, open the aperture a stop, or raise ISO a stop — whichever won't ruin your creative intent. Reshoot, recheck. Two or three frames in, you're dialed.



Do this once and it sticks

Set up a still scene indoors. In full manual, get a correct exposure. Now change *one* control by a stop and rebalance with another to keep the same brightness — e.g. open aperture one stop, speed up shutter one stop. Same brightness, different look. Do it five times. You'll feel the see-saw in your hands.



Manual + changing light = frustration

Full manual shines when light is constant. Out on a partly-cloudy walk where the sun keeps ducking behind clouds, manual makes you re-meter constantly. That's exactly when a priority mode or Auto ISO earns its keep. Match the mode to the conditions.

CHAPTER 8

12 Real-World Settings Recipes

Theory is nothing without a starting point in the field. These twelve recipes are your cheat sheet — reliable jumping-off settings for the scenes beginners shoot most. They are *starting points*, not laws. Set them, check your meter and histogram, and adjust a stop as needed. Screenshot this chapter for your phone.

1 • Bright outdoor portrait

APERTURE PRIORITY

Aperture **f/2.8**

Shutter **1/500s**

ISO **100**

Blurred background, subject pops. Focus the near eye. Shade or golden hour beats harsh noon light. Open to f/1.8 for more blur.

2 • Indoor party / birthday

FULL MANUAL + AUTO ISO

Aperture **f/2.0**

Shutter **1/160s**

ISO **Auto ≤6400**

Open wide to drink in the dim light, keep shutter fast enough to freeze mingling people, let Auto ISO fill the gap. Find a lamp or window and put faces toward it.

3 • Sunset / golden hour

APERTURE PRIORITY

Aperture **f/8**

Shutter **1/125s**

ISO **100**

Meter for the sky, then dial -1 exposure compensation to keep those rich colors from washing out. A silhouetted subject in front looks magical.

4 • Kids' / outdoor sports

SHUTTER PRIORITY

Aperture **Auto (~f/4)**

Shutter **1/1000s**

ISO **Auto ≤6400**

Freeze the action, use Continuous AF (AF-C / AI Servo) and burst mode. Track the near eye. Overcast? The camera will raise ISO — let it.

5 · Silky waterfall / stream

TRIPOD · MANUAL

Aperture **f/16**

Shutter **1s**

ISO **100**

Tripod essential. Use the 2-second timer so pressing the shutter doesn't shake it. Bright day? Add a neutral-density filter to reach that slow shutter.

6 · Sweeping landscape

APERTURE PRIORITY

Aperture **f/11**

Shutter **1/125s**

ISO **100**

Deep front-to-back sharpness. Focus a third of the way in. On a tripod, drop the shutter and keep ISO at base for the cleanest file.

7 · Night street scene

MANUAL

Aperture **f/2.8**

Shutter **1/125s**

ISO **3200**

Open wide, accept high ISO, keep the shutter fast enough for people. Expose for the lit areas and let shadows fall dark — night is *supposed* to look dark.

8 · Pet in action

SHUTTER PRIORITY

Aperture **Auto (~f/4)**

Shutter **1/800s**

ISO **Auto ≤6400**

Get low to their eye level. Continuous AF, burst mode, focus the eyes. Fast, unpredictable motion loves a fast shutter and a lot of frames.

9 · Product / food on a table

APERTURE PRIORITY

Aperture **f/5.6**

Shutter **1/125s**

ISO **200**

Near the sweet spot for sharpness with a gentle background blur. Big soft window light to the side. Steady the camera on the table if the shutter dips slow.

10 · Concert / stage

MANUAL

Aperture **f/2.8**

Shutter **1/250s**

ISO **6400**

Bright stage lights, black surroundings — meter off the performer with spot metering, or the dark background will trick the camera into overexposing.

11 · Snow / bright beach

APERTURE PRIORITY + COMP

Aperture **f/8**

Shutter **1/500s**

ISO **100**

Dial in +1.5 to +2 exposure compensation or the meter renders white snow a dull gray. Check the histogram — push it right without clipping.

12 · Backlit subject (window/sun behind)

APERTURE PRIORITY + COMP

Aperture **f/2.8**

Shutter **1/250s**

ISO **400**

Add +1 to +2 compensation so your subject isn't a silhouette, or spot-meter their face. That bright rim of light around them is a gift — use it.

The one-glance summary table

Scene	Mode	Aperture	Shutter	ISO
Outdoor portrait	A / Av	f/2.8	1/500s	100
Indoor party	M + Auto ISO	f/2.0	1/160s	Auto
Sunset	A / Av	f/8	1/125s	100
Sports	S / Tv	auto	1/1000s	Auto
Waterfall	M (tripod)	f/16	1s	100
Landscape	A / Av	f/11	1/125s	100
Night street	M	f/2.8	1/125s	3200
Pet action	S / Tv	auto	1/800s	Auto
Product / food	A / Av	f/5.6	1/125s	200
Concert	M (spot)	f/2.8	1/250s	6400
Snow / beach	A / Av +2	f/8	1/500s	100
Backlit	A / Av +1.5	f/2.8	1/250s	400

CHAPTER 9

Practice Drills & Next Steps

Reading built the map; only shooting builds the muscle. Spend this weekend on three short drills and the exposure triangle stops being knowledge and becomes instinct — the kind that lets you set your camera without looking down.

Drill 1 — The aperture ladder (30 minutes)

Sit a friend or a plant six feet in front of a cluttered background. In Aperture Priority, shoot the same frame at f/1.8 (or your widest), f/2.8, f/5.6, f/8, and f/16. Line them up on your computer. *Watch the background go from melted to crisp.* You will never again wonder what aperture does.

Drill 2 — The shutter ladder (20 minutes)

Have someone walk past you left to right. In Shutter Priority, shoot them at 1/30s, 1/125s, 1/250s, 1/500s, and 1/1000s. Compare. You'll see exactly where blur turns to freeze — and learn how fast "walking speed" really needs.

Drill 3 — The full-manual balance (30 minutes)

Pick one indoor scene. In full Manual, nail a correct exposure using the six-step routine from Chapter 7. Then, keeping the brightness identical, find three *different* combinations of aperture, shutter, and ISO that all meter at zero. Notice how each looks different. This is the see-saw, in your hands, for real.

Your printable "too dark / too bright" reminder

When a shot's brightness is off and you're not sure which knob to turn, walk this flowchart. It's the whole book compressed into a field card.

1

Photo too DARK? → First, can you slow the shutter?

If it's still above your handholding minimum and the subject isn't moving, slow it a stop. More light, no downside.

2

Still too dark, but shutter can't go slower? → Open the aperture.

Drop to a lower f-number for more light — as long as you can accept the shallower depth of field.

3**Aperture already wide open? → Raise the ISO.**

Bump it a stop or two. A little grain is nothing next to a properly bright, sharp photo.

4**Photo too BRIGHT? → Reverse the order.**

First lower ISO toward base, then narrow the aperture (higher f-number), then speed up the shutter. Pull light out from the cheapest side effect first.

5**In a priority mode and it's consistently off? → Use exposure compensation.**

Snow or backlight fooling the meter: add light (+). Dark subject going muddy gray: subtract light (-). Then confirm with the histogram.

**The one upgrade worth making**

If you own only a kit zoom, a 50mm f/1.8 "nifty fifty" — often under \$150 — is the highest-impact purchase in beginner photography. It gathers far more light for low-light shots and produces the beautiful background blur that makes portraits sing. It teaches you aperture faster than any lens.

**Shoot in RAW while you learn**

Switch your file format to RAW (or RAW+JPEG). RAW files hold far more recoverable detail in shadows and highlights, so a slightly-off exposure while you're learning is easily rescued in editing. It's a safety net that costs you nothing but card space.

The dial has five real settings and three real controls. That's the entire mountain. You just climbed it.

You started this weekend afraid of a dial. You're ending it able to look at any scene, decide what the photo is *about*, and set three controls to make it happen on purpose. That's not a beginner's skill. That's the skill. Everything else in photography — lighting, composition, editing — builds on the foundation you just poured. Go fill a memory card. Make mistakes on purpose. Read your histograms. In a month, Auto mode will feel like a language you used to speak before you learned to actually talk.

REMEMBER

You don't take the picture the camera decides on anymore — you decide, and the camera obeys. That's what getting off Auto really means.

Story Mode Guy

Photography guides for people who treat everything like it has a plot. · storymodeguy.com