



Lab Number: 09

Date: 2025/08/17

## Title: Basic router configuration and static routing in Packet Tracer

### Theory:

#### a) Router

A router is a network device that forwards data packets between computer networks. Routers perform traffic directing functions on the Internet. A packet is typically forwarded from one router to another through the networks that constitute the internetwork until it reaches its destination node.

#### b) Network Diagram




Fig: Network diagram including router and switch

### Implementation Sequence

Here is the implementation sequence for Basic router configuration and static routing in Packet Tracer.

#### a. Basic router Configuration

##### i. Configuring Global Parameters

Here are the steps to configure global parameters on a router:

**Step 1: Open Packet Tracer and set up the devices (routers, PCs).**





Fig: Simple Network setup

## Step 2: Access the Router CLI

Use the console cable to access the router's command-line interface (CLI)



The screenshot shows the Cisco Packet Tracer interface with the title "Cisco Packet Tracer - C:\Users\dell\Abinash Regmi". Below the title, it says "Router0-abinash". The tab bar at the top has "Physical", "Config", "CLI" (which is selected), and "Attributes". The main area is titled "IOS Command Line Interface". It displays the following text:

```
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2012 by Cisco Systems, Inc.
Compiled Thurs 5-Jan-12 15:41 by pt_team
Image text-base: 0x2100F918, data-base: 0x24729040

This product contains cryptographic features and is subject to United
States and local country laws governing import, export, transfer and
use. Delivery of Cisco cryptographic products does not imply
third-party authority to import, export, distribute or use encryption.
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html

If you require further assistance please contact us by sending email to
export@cisco.com.

Cisco CISCO1941/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
2 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---
```

Fig: Accessing Router Command-Line Interface via Console Cable

## Step 3: Configure Terminal

Type enable to enter privileged EXEC mode and use configure terminal to access global configuration mode.

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
```

Fig: Entering Privileged EXEC and Global Configuration Mode on the Router

## Step 4: Set a hostname for the router

Use the command hostname [RouterName] to assign a name to the router.

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname router1
```

Fig: Setting the Hostname on the Router

## Step 5: Configure a Password for Privileged Mode

Set an enable password using Router(config)#enable secret [password]

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname router1
router1(config)#enable secret 9803068643
router1(config)#

```

Fig: Configuring a Password

## ii. Configuring Gigabit Ethernet

Here are the steps to configure gigabit Ethernet interfaces on a router:

### Step 1: Configure Terminal

Type enable to enter privileged EXEC mode and use configure terminal to access global configuration mode.

```
router1#enable
router1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
router1(config)#

```

Fig: Entering Privileged EXEC and Global Configuration Mode on Router

### Step 2: Access the interface configuration mode

Use the command interface <interface\_name> to enter the configuration mode for a specific router interface.

```
router1(config)#interface GigabitEthernet0/1

```

Fig: Accessing the interface configuration mode

### Step 3: Assign an IP address

Once in the interface configuration mode, assign a unique IP address and subnet mask to the interface using the Ip address command.

```
router1(config)#interface GigabitEthernet0/1
router1(config-if)#ip address 111.111.11.1 255.255.0.0
router1(config-if)#

```

Fig: Enabling the Gigabit Ethernet Interface on Router

### Step 4: Enable the interface

After assigning an IP address, use the no shutdown command to activate the interface.

By default, router interfaces are in a “shutdown” state.

```
router1(config)#interface GigabitEthernet0/1
router1(config-if)#ip address 111.111.11.1 255.255.0.0
router1(config-if)#no shutdown

router1(config-if)#


```

Fig: Enabling the Gigabit Ethernet Interface on a Router

## b. Static Routing Configuration

### i. Configuring Network (PCs and Routers)

#### Network Diagram



#### Configuring PCs

##### Step 1: Assign IP addresses to the PC's

Configure the IP addresses on the PCs within the same network as their respective router's interface.




Fig: Assigning IP address to PC's

## Configuring Routers

### **Step 1: Set the IP address on the Gigabit Ethernet interface**

## For router0

```
Router>enable
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface GigabitEthernet0/0
Router(config-if)#ip address 44.4.4.3 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/1
Router(config-if)#ip address 43.3.3.3 255.0.0.0
Router(config-if)#exit
```


fig: Configuring IP Address on Gigabit Ethernet Interface

**For router1**

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface GigabitEthernet0/0
Router(config-if)#ip address 45.3.3.3 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/1
Router(config-if)#ip address 44.3.3.2 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
Router(config)#
```

Fig: Configuring IP Address on Gigabit Ethernet Interface

## **Step 2: Checking Router is working or not**



```

PC1-abinash

Physical Config Desktop Programming Attributes

Command Prompt

Pinging 43.4.4.4 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 43.4.4.4:
  Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>exit

```

Fig: Router Connectivity Test Failure

Above figure shows two failed ping attempts from different PCs to check connectivity. Both PCs are trying to reach different IPs (44.3.3.4 and 55.4.4.5), but the destination hosts are unreachable. The error message 100% packet loss indicate a problem with the router's configuration or connection between networks. This suggests that the router is not routing packets correctly between these networks.

### Step 3: Adding a static route

Adding a static route to Router R1's network

```

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 44.0.0.0 255.0.0.0 44.4.4.3
%Invalid next hop address (it's this router)
Router(config)#ip route 44.0.0.0 255.0.0.0 44.3.3.2
Router(config)#ip route 45.0.0.0 255.0.0.0 44.3.3.2
Router(config)#

```

Fig: Adding Static Route to Router 1 Network

Add a static route to Router R0's network

```

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 44.0.0.0 255.0.0.0 44.4.4.3
Router(config)#ip route 43.0.0.0 255.0.0.0 44.4.4.3
Router(config)#

```

Fig: Adding Static Route to Router R0 Network

### ii. Testing and Validation

From each PC, use the ping command to test connectivity to a PC in a different network.

```

Cisco Packet Tracer - C:\Users\dell\Abinash Regmi
PC0-abinash

Physical Config Desktop Programming Attributes

Command Prompt


Cisco Packet Tracer PC Command Line 1.0
C:\>ping 45.3.3.4

Pinging 45.3.3.4 with 32 bytes of data:

Reply from 45.3.3.4: bytes=32 time=18ms TTL=128
Reply from 45.3.3.4: bytes=32 time=12ms TTL=128
Reply from 45.3.3.4: bytes=32 time<1ms TTL=128
Reply from 45.3.3.4: bytes=32 time=12ms TTL=128

Ping statistics for 45.3.3.4:
  Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
  Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 18ms, Average = 10ms
C:\>exit

```



The screenshot shows the Cisco Packet Tracer interface with the title bar "PC1-abinash". The menu bar includes "Physical", "Config", "Desktop" (which is underlined), "Programming", and "Attributes". A sub-menu "Command Prompt" is open, displaying the output of a ping command. The output shows four successful replies from the target IP 43.4.4.4 with TTL=128, times ranging from 2ms to 14ms. It also provides ping statistics: Sent = 4, Received = 4, Lost = 0 (0% loss). The command prompt ends with "C:\>".

```

Cisco Packet Tracer PC Command Line 1.0
C:\>ping 43.4.4.4

Pinging 43.4.4.4 with 32 bytes of data:

Reply from 43.4.4.4: bytes=32 time=2ms TTL=128
Reply from 43.4.4.4: bytes=32 time=11ms TTL=128
Reply from 43.4.4.4: bytes=32 time=13ms TTL=128
Reply from 43.4.4.4: bytes=32 time=14ms TTL=128

Ping statistics for 43.4.4.4:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 14ms, Average = 10ms

C:\>

```

Fig: Testing Connectivity Between PC's Using Ping Commands

The above shows successful ping tests between two PCs in different networks. PC0 pings 45.3.3.4 with no packet loss and low latency, while PC1 pings 43.4.4.4 with similar successful results. This confirms network connectivity between the PCs.

### **Addressing Table:**

The addressing table of the static routing is as follows:

Device	Interface	IPv4 Address	Subnet	Default Gateway
PC0	NIC	43.4.4.4	255.0.0.0	43.3.3.3
PC1	NIC	45.3.3.4	255.0.0.0	45.3.3.3

### **Conclusion**

This lab introduced basic router configuration and static routing using Cisco Packet Tracer. We successfully set up routers and configured static routes, enabling communication between PCs on different networks. This exercise demonstrated essential network configuration skills and the importance of routing in ensuring connectivity.