

Add hosts and install plug-in packages on remote hosts

SnapCenter Software

Nirupama Sriram, Soumik Das, Archana June 16, 2021

Table of Contents

Add hosts and install plug-in packages on remote hosts.	
---	--

Add hosts and install plug-in packages on remote hosts

You must use the SnapCenterAdd Host page to add hosts, and then install the plug-in packages. The plug-ins are automatically installed on the remote hosts. You can add a host and install the plug-in packages either for an individual host or for a cluster.

What you will need

- You must be a user that is assigned to a role that has the plug-in install and uninstall permissions, such as the SnapCenter Admin role.
- You should ensure that the message queueing service is running.
- If you are using group Managed Service Account (gMSA), you should configure gMSA with administrative privileges.

Configure group Managed Service Account on Windows Server 2012 or later for custom applications

About this task

You cannot add a SnapCenter Server as a plug-in host to another SnapCenter Server.

If you install plug-ins on a cluster (WSFC), the plug-ins are installed on all of the nodes of the cluster.

Steps

- 1. In the left navigation pane, click **Hosts**.
- 2. Verify that the **Managed Hosts** tab is selected at the top.
- 3. Click Add.
- 4. On the **Hosts** page, perform the following actions:

For this field	Do this
Host Type	Select the host type:
	• Windows
	• Linux
	The custom plug-ins can be used in both Windows and Linux environments.

Do this
Enter the fully qualified domain name (FQDN) or the IP address of the host.
SnapCenter depends on the proper configuration of the DNS. Therefore, the best practice is to enter the FQDN.
For Windows environments, the IP address is supported for untrusted domain hosts only if it resolves to the FQDN.
You can enter the IP addresses or FQDN of a stand-alone host.
If you are adding a host by using SnapCenter and the host is part of a subdomain, you must provide the FQDN.
Either select the credential name that you created, or create new credentials.
The credentials must have administrative rights on the remote host. For details, see the information about creating credentials.
You can view details about the credentials by positioning your cursor over the credential name that you specified.
The credentials authentication mode is determined by the host type that you specify in the Add Host wizard.

- 5. In the **Select Plug-ins to Install** section, select the plug-ins to install.
- 6. (Optional) Click More Options.

For this field	Do this
Port	Either retain the default port number, or specify the port number.
	The default port number is 8145. If the SnapCenter Server was installed on a custom port, that port number will be displayed as the default port.
	If you manually installed the plugins and specified a custom port, you must specify the same port. Otherwise, the operation fails.
Installation Path	The custom plug-ins can be installed on either a Windows system or a Linux system.
	 For the SnapCenter Plug-ins Package for Windows, the default path is C:\Program Files\NetApp\SnapCenter.
	Optionally, you can customize the path.
	 For SnapCenter Plug-ins Package for Linux, the default path is /opt/NetApp/snapcenter.
	Optionally, you can customize the path.
	For the SnapCenter Custom Plug-ins:
	 i. In the Custom Plug-ins section, click Browse, and then select the zipped custom plug-in folder.
	The zipped folder contains the custom plug- in code and the descriptor .xml file.
	ii. Click Upload .
	The descriptor .xml file in the zipped custom plug-in folder is validated before the package is uploaded.
	The custom plug-ins that are uploaded to the SnapCenter Server are listed.
	If you want to manage MySQL or DB2 applications, you can use the MySQL and DB2 custom plug-ins that are provided by NetApp. The MySQL and DB2 custom plugins are available at the NetApp Tool Chest.
	NetApp Automation Store

For this field	Do this	
Skip preinstall checks	Select this check box if you already installed the plug-ins manually and you do not want to validate whether the host meets the requirements for installing the plug-in.	
Use group Managed Service Account (gMSA) to run the plug-in services	For Windows host, select this check box if you want to use group Managed Service Account (gMSA) to run the plug-in services.	
	Provide the gMSA name in the following format: domainName\accountName\$.	
	gMSA will be used as a log on service account only for SnapCenter Plug-in for Windows service.	

7. Click Submit.

If you have not selected the **Skip prechecks** checkbox, the host is validated to verify whether the host meets the requirements for installing the plug-in. The disk space, RAM, PowerShell version, .NET version, location (for Windows plug-ins), and Java version (for Linux plug-ins) are validated against the minimum requirements. If the minimum requirements are not met, appropriate error or warning messages are displayed.

If the error is related to disk space or RAM, you can update the web.config file located at C:\Program Files\NetApp\SnapCenter WebApp to modify the default values. If the error is related to other parameters, you must fix the issue.



In an HA setup, if you are updating web.config file, you must update the file on both nodes.

8. If host type is Linux, verify the fingerprint, and then click Confirm and Submit.

In a cluster setup, you should verify the fingerprint of each of the nodes in the cluster.



Fingerprint verification is mandatory even if the same host was added earlier to SnapCenter and the fingerprint was confirmed.

Monitor the installation progress.

The installation-specific log files are located at /custom location/snapcenter/logs.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.