CX

Generated by Doxygen 1.8.6

Tue Mar 4 2014 23:02:55

ii CONTENTS

Contents

1	Main	n Page	2
	1.1	Installation	
	1.2	Examples and Tutorials	2
2	Bloc	cking Code	3
3	Mod	ules	4
4	Prog	gram Model	4
5	licen	ise	6
6	Mod	ule Index	6
	6.1	Modules	6
7	Nam	nespace Index	6
	7.1	Namespace List	6
8	Hiera	archical Index	7
	8.1	Class Hierarchy	7
9	Clas	es Index	9
	9.1	Class List	9
10	File I	Index	10
	10.1	File List	10
11	Mod	ule Documentation	12
	11.1	Data	12
		11.1.1 Detailed Description	12
	11.2	Entry Point	13
		11.2.1 Detailed Description	13
		11.2.2 Function Documentation	13
		11.2.3 Variable Documentation	13
	11.3	Error Logging	14
		11.3.1 Detailed Description	14
		11.3.2 Enumeration Type Documentation	14
	11.4	Input Devices	15
		11.4.1 Detailed Description	15
	11.5	Randomization	16

		44 - 4	Detailed Description		40
			Detailed Description		
	11.6		D. 11 D. 12		
			Detailed Description		
	11.7				
			Detailed Description		
			Variable Documentation		
	11.8				
			Detailed Description		
	11.9				
		11.9.1	Detailed Description	٠.	20
12	Nam	espace [Documentation		21
			nespace Reference		21
			Detailed Description		
	12.2		o Namespace Reference		
			Detailed Description		
			Function Documentation		
	12.3		aw Namespace Reference		
			Detailed Description		
			Function Documentation		
	12.4		tances Namespace Reference		
			Detailed Description		
	12.5		vate Namespace Reference		
			Detailed Description		
	12.6		nth Namespace Reference		
		_	Detailed Description		
	12.7		I Namespace Reference		
			Detailed Description		
			Function Documentation		
13	Clas	s Docum	mentation		32
	13.1	CX::Syn	nth::Adder Class Reference		32
		13.1.1	Detailed Description		33
		13.1.2	Member Function Documentation		33
	13.2	CX::Syn	nth::AdditiveSynth Class Reference		33
		13.2.1	Detailed Description		34
		13.2.2	Member Function Documentation		34
	13.3	CX::Syn	nth::Clamper Class Reference		36

v CONTENTS

13.3.1 Detailed Description
13.3.2 Member Function Documentation
13.4 CX::CX_SoundStream::Configuration Struct Reference
13.4.1 Detailed Description
13.4.2 Member Data Documentation
13.5 CX::CX_SlidePresenter::Configuration Struct Reference
13.5.1 Detailed Description
13.6 CX::CX_Clock Class Reference
13.6.1 Detailed Description
13.6.2 Member Function Documentation
13.7 CX::Util::CX_CoordinateConverter Class Reference
13.7.1 Detailed Description
13.7.2 Constructor & Destructor Documentation
13.7.3 Member Function Documentation
13.8 CX::CX_DataFrame Class Reference
13.8.1 Detailed Description
13.8.2 Member Function Documentation
13.9 CX::CX_DataFrameCell Class Reference
13.9.1 Detailed Description
13.9.2 Constructor & Destructor Documentation
13.9.3 Member Function Documentation
13.10CX::CX_DataFrameColumn Class Reference
13.10.1 Detailed Description
13.11CX::CX_DataFrameRow Class Reference
13.11.1 Detailed Description
13.12CX::Util::CX_DegreeToPixelConverter Class Reference
13.12.1 Detailed Description
13.12.2 Constructor & Destructor Documentation
13.12.3 Member Function Documentation
13.13CX::CX_Display Class Reference
13.13.1 Detailed Description
13.13.2 Member Function Documentation
13.14CX::CX_InputManager Class Reference
13.14.1 Detailed Description
13.14.2 Member Function Documentation
13.15CX::CX_Joystick Class Reference
13.15.1 Detailed Description

13.15.2 Member Function Documentation
13.16CX::CX_Keyboard Class Reference
13.16.1 Detailed Description
13.16.2 Member Function Documentation
13.17CX::Util::CX_LengthToPixelConverter Class Reference
13.17.1 Detailed Description
13.17.2 Constructor & Destructor Documentation
13.17.3 Member Function Documentation
13.18CX::CX_Logger Class Reference
13.18.1 Detailed Description
13.18.2 Member Function Documentation
13.19CX::CX_Mouse Class Reference
13.19.1 Detailed Description
13.19.2 Member Function Documentation
13.20CX::CX_RandomNumberGenerator Class Reference
13.20.1 Detailed Description
13.20.2 Constructor & Destructor Documentation
13.20.3 Member Function Documentation
13.21CX::CX_SlidePresenter Class Reference
13.21.1 Detailed Description
13.21.2 Member Enumeration Documentation
13.21.3 Member Function Documentation
13.22CX::CX_SoundObject Class Reference
13.22.1 Detailed Description
13.22.2 Member Function Documentation
13.23CX::CX_SoundObjectPlayer Class Reference
13.23.1 Detailed Description
13.23.2 Member Function Documentation
13.24CX::CX_SoundObjectRecorder Class Reference
13.24.1 Detailed Description
13.24.2 Member Function Documentation
13.25CX::CX_SoundStream Class Reference
13.25.1 Detailed Description
13.25.2 Member Function Documentation
13.26CX::Util::CX_TrialController Class Reference
13.26.1 Detailed Description
13.26.2 Member Function Documentation

vi CONTENTS

13.27CX::Synth::Envelope Class Reference
13.27.1 Detailed Description
13.27.2 Member Function Documentation
13.28CX::CX_Mouse::Event Struct Reference
13.28.1 Detailed Description
13.28.2 Member Enumeration Documentation
13.29CX::CX_Joystick::Event Struct Reference
13.29.1 Detailed Description
13.29.2 Member Enumeration Documentation
13.30CX::CX_Keyboard::Event Struct Reference
13.30.1 Detailed Description
13.30.2 Member Enumeration Documentation
13.30.3 Member Data Documentation
13.31CX::CX_SlidePresenter::FinalSlideFunctionArgs Struct Reference
13.31.1 Detailed Description
13.32CX::Synth::FIRFilter Class Reference
13.32.1 Detailed Description
13.32.2 Member Function Documentation
13.33CX::CX_SoundStream::InputEventArgs Struct Reference
13.33.1 Detailed Description
13.34CX::Synth::Mixer Class Reference
13.34.1 Detailed Description
13.34.2 Member Function Documentation
13.35CX::Synth::ModuleBase Class Reference
13.35.1 Detailed Description
13.35.2 Member Function Documentation
13.35.3 Friends And Related Function Documentation
13.36CX::Synth::Multiplier Class Reference
13.36.1 Detailed Description
13.36.2 Member Function Documentation
13.37CX::Synth::Oscillator Class Reference
13.37.1 Detailed Description
13.37.2 Member Function Documentation
13.38CX::CX_SoundStream::OutputEventArgs Struct Reference
13.38.1 Detailed Description
13.39CX::CX_SlidePresenter::PresentationErrorInfo Struct Reference
13.39.1 Detailed Description

	13.39.2 Member Data Documentation	107
1	3.40CX::Synth::RCFilter Class Reference	107
	13.40.1 Detailed Description	108
	13.40.2 Member Function Documentation	108
1	3.41CX::Synth::RecursiveFilter Class Reference	108
	13.41.1 Detailed Description	109
	13.41.2 Member Function Documentation	109
1	3.42CX::CX_SlidePresenter::Slide Struct Reference	109
	13.42.1 Detailed Description	110
	13.42.2 Member Enumeration Documentation	110
	13.42.3 Member Data Documentation	110
1	3.43CX::CX_SlidePresenter::SlideTimingInfo Struct Reference	110
	13.43.1 Detailed Description	110
	13.43.2 Member Data Documentation	111
1	3.44CX::Synth::SoundObjectInput Class Reference	111
	13.44.1 Detailed Description	111
	13.44.2 Member Function Documentation	111
1	3.45CX::Synth::SoundObjectOutput Class Reference	112
	13.45.1 Detailed Description	112
1	3.46CX::Synth::Splitter Class Reference	112
	13.46.1 Detailed Description	113
	13.46.2 Member Function Documentation	113
1	3.47CX::Synth::StereoSoundObjectOutput Class Reference	113
	13.47.1 Detailed Description	113
1	3.48CX::Synth::StereoStreamOutput Class Reference	114
	13.48.1 Detailed Description	114
1	3.49CX::Synth::StreamOutput Class Reference	114
	13.49.1 Detailed Description	115
44 5	Tile De componentation	445
		115
ı	4.1 advancedChangeDetectionTask.cpp File Reference	
	14.1.1 Detailed Description	
1	4.2 basicChangeDetectionTask.cpp File Reference	
	14.2.1 Detailed Description	
1	4.3 nBack.cpp File Reference	
	14.3.1 Detailed Description	117
Inde	x	118

1 Main Page

of xCX (hereafter referred to as CX) is a "total conversion mod" for openFrameworks (often abbreviated oF) that is designed to be used used for creating psychology experiments.

The most well-organized way to access the documentation is go to the Modules page. The best way to get an overview of how CX works is to look at the Examples and Tutorials.

To learn about presenting visual stimuli, go to the Video page.

To learn about auditory stimuli, go to the Sound page.

To learn how to store and output experiment data, see the Data page.

To learn about random number generation, see the Randomization page.

To learn about how CX logs errors and other runtime information, see the Error Logging page.

1.1 Installation

In order to use CX, you must have openFrameworks installed. See http://openframeworks.cc/download/to download openFrameworks. Currently only version 0.8.0 of openFrameworks is supported by CX.

Once you have installed openFrameworks, you can install CX by putting the contents of the CX repository into a subdirectory under openFrameworksDirectory/addons (typically openFrameworksDirectory/addons/ofxCX), where open-FrameworksDirectory is where you put openFramworks when you installed it.

To use CX in a project, use the openFrameworks project generator and select ofxCX as an addon. The project generator can be found in openFrameworksDirectory/projectGenerator.

In order to use the examples, do the following:

- Use the oF project generator (in openFrameworksDirectory/projectGenerator) to create a new project that uses the ofxCX addon.
- 2. Go to the newly-created project directory (that you chose when creating the project in step 1) and go into the src subdirectory.
- 3. Delete all of the files in the src directory (main.cpp, testApp.h, and testApp.cpp). 4a. Copy the example .cpp file into this directory. 4b. If the example has a data folder, copy the contents of that folder into yourProject-Directory/bin/data. bin/data folders probably won't exist at this point. You can create them.
- 4. This step depends on your compiler, but you'll need to tell it to use the example source file that you copied in step 4a when it compiles the project (and possibly to specifically not use the files you deleted from the src directory in step 3).
- 5. Compile and run the project.

1.2 Examples and Tutorials

There are several examples that serve as tutorials for CX. Some of the examples are on a specific topic and others are sample experiments that integrate together different features of CX. The example files can be found in the CX directory (see Installation) in subfolders with names beginning with "example-".

Tutorials:

 soundObject - Tutorial covering a number of things that you can do with CX_SoundObjects, including loading sound files, combining sounds, and playing them. 2 Blocking Code 3

dataFrame - Tutorial covering use of CX_DataFrame, which is a container for storing data that is collected in an
experiment.

· logging - Tutoral explaining how the error logging system of CX works and how you can use it in your experiments.

Experiments:

- basicChangeDetection A very straightforward change-detection task demonstrating some of the features of CX like presentation of time-locked stimuli, keyboard response collection, and use of the CX_RandomNumber-Generator.
- advancedChangeDetection This example expands on basicChangeDetection, including CX_DataFrame and C-X_TrialController in order to simplify the experiment.
- nBack Demonstrates advanced use of CX SlidePresenter in the implementation of an N-Back task.

Misc.:

- helloWorld A very basic getting started program.
- animation A simple example of the most simple way to draw moving things in CX. Also includes some mouse stuff: cursor movement, clicks, and scroll wheel activity.
- renderingTest Includes several examples of how to draw stuff using ofPath (arbitrary lines), ofTexture (a kind of pixel buffer), ofImage (for opening image files: .png, .jpg, etc.), a variety of basic oF drawing functions (ofCircle, ofRect, ofTriangle, etc.), and a number of CX drawing functions from the CX::Draw namespace.

2 Blocking Code

Blocking code is code that either takes a long time to complete or that waits until some event occurs before allowing code execution to continue. An example of blocking code that waits is

```
do {
    Input.pollEvents();
} while (Input.Keyboard.availbleEvents() == 0);
```

This code waits until the keyboard has been used in some way. No code past it can be executed until the keyboard is used, which could take a long time. Any code that blocks while waiting for a human to do something is blocking.

An example of blocking code that takes a long time (or at least could take a long time) is

```
vector<double> d = CX::Util::sequence<double>(0, 1000000, .033);
```

which requires the allocation of about 300 MB of RAM. This code doesn't wait for anything to happen, it just takes a long time to execute.

Blocking code is potentially harmful because it prevents some parts of CX from working in some situations. It is not a cardinal sin and there are times when using blocking code is acceptable. However, blocking code should not be used when trying to present stimuli or when responses are being made. The reason for this is that CX expects to be able to repeatedly check information related to stimulus presentation and input at very short intervals (at least every millisecond), but that cannot happen if a piece of code is blocking. There is of course an exception to the "no blocking while waiting for responses" rule, which is when your blocking code is doing nothing but waiting for a response and constantly polling for user input. For example, the following code waits until any response is made:

```
while(!Input.pollEvents())
;
```

3 Modules

4 Program Model

One of the foundational aspects of CX is the design of the overall program flow, which includes things such as how responses are collected, how stimuli are drawn to the screen, and other similar concepts.

The most important thing to understand is that in CX, nothing happens that your code does not explicitly ask for, with the exception of a small amount of setup, which is discussed below. For example, CX does not magically collect and timestamp user responses for you. Your code must poll for user input in order to get timestamps for input. This is explained more in the input section. In CX, there is no code running in the background that makes everything work out for your experiment, you have to design your experiment in such a way that you are covering all of your bases. That said, CX is specifically designed to make doing that as easy and painless as possible, while still giving you as much control over your experiment as is reasonably possible.

Internals

CX is not a monolithic entity. It is based on a huge amount of open source software written by many different authors over the years. Clearly, CX is based on openFrameworks, but openFramworks itself is based on many different libraries. Window handling, which involves creating a window that can be rendered to and receiving user input events from the operating system, is managed by GLFW (http://www.glfw.org/). The actual rendering is visual stimuli is done using OpenGL (http://www.opengl.org/), which is wrapped by several openFrameworks abstractions (e.g. of-GLProgrammableRenderer at a lower level, e.g. ofPath at the level at which a typical user would use).

Audio is processed in different ways depending on the type of audio player used. CX_SoundObjectPlayer wraps CX_SoundStream which wraps RtAudio (https://www.music.mcgill.ca/~gary/rtaudio/). If you are using ofSoundPlayer, depending on your operating system it might eventually use FMOD on Windows or OSx (http-://www.fmod.org/; although the openFrameworks maintainers are considering moving away from FMOD) or OpenAL on Linux (http://en.wikipedia.org/wiki/OpenAL). However, you should check that this information is correct.

Overriding openFrameworks

Although CX is technically an addon to openFrameworks, there are a number of ways in which CX hijacks normal oF functionality in order to work better. As such, you cannot assume that all oF functionality is available to you.

Generally, drawing visual stimuli using oF classes and functions is fully supported. See the renderingTest example to see a pletora of ways to put things on the screen.

Audio output using of Sound Player is supported, although no timing guarantees are made.

The input events (e.g. ofEvents().mousePressed) technically work, but with two serious limitations. 1) The events only fire when CX_InputManager::pollEvents() is called (which internally calls glfwPollEvents() to actually kick off the events firing). 2) The standard oF events do not have timestamps, which limits their usefulness.

Pre-experiment Setup

There is very little that CX does without you asking for it. The one major exception is pre-experiment setup, in which a number of basic operations are performed in order to set up a platform on which the rest of the experiment can run.

The most significant step is to open a window and set up the OpenGL rendering environment.

4 Program Model 5

Input

The way user input is handled by CX is easily explained by giving the process of receiving a mouse click. Assume that a CX program is running in a window. The user clicks inside of the window. At this point, the operating system (or at least the windowing subsystem of the operating system, but I will choose to conflate them) detects that the click has occured and notes that the location of the click is within the window. The operating system then attempts to tell the program that a mouse click has occured. In order to be notified about input events like mouse click, the program has previously set up a message queue for incoming messages from the operating system. The OS puts the mouse event into the message queue. In order for the program to find out about the message it needs to check to message queue. This is what happens when CX::CX_InputManager::pollEvents() is called: The message queue is checked and all messages in the queue are processed, given timestamps, and routed to the next queue (e.g. the message queue in CX::CX_Mouse that is accessed with CX::CX_Mouse::availableEvents() and CX::CX_Mouse::getNextEvent()). The timestamps are not given by the operating system*, so if pollEvents is not called regularly, input events will be received and everything will appear to be working correctly, but the timestamps will be wrong.

Of course, the actual process extends all the way back to the input device itself. The user presses the button and the microcontroller in the input device senses that a button has been pressed. It places this button press event into its outgoing message queue. At the next polling interval (typically 1 ms), the USB host controller on the computer polls the device for messages, discovers that a message is waiting and copies the message to the computer. At some point, the operating system checks to see if the USB host controller has received messages from any devices. It discovers the message and moves the message into the message queue of the program. At each step in which the message moves from one message queue to the next, the data contained in the message likely changes a little. At the start in the mouse, the message might just be "button 1 pressed". At the next step in the USB host controller, the message might be "input device 1 (type is mouse) button 1 pressed". Once the operating system gets the message it might be "mouse button 1 pressed while cursor at (367, 200) relative to clicked window". Eventually, the message gets into the message queue that users of CX work with, in CX::CX Mouse, for example.

This process sounds very long and complicated, suggesting that it might take a long time to complete, throwing off timing data. That is true: Input timing data collected by CX is not veridical, there are invariably delays, including non-systematic delays. However, there are several steps in the process that no experiment software can get around, so the problems with timing data are not unique to CX. It might be possible to write a custom driver for the mouse or keyboard that allows the software to bypass the operating system's message queue, but it is very difficult to avoid the USB hardware delays, which can be on the order of milliseconds for many kinds of standard input devices. The next layer of the problem is that we are really interested in response time to a specific stimulus, but the time at which the stimulus was actually presented may be misreported by audio or video hardware/software, so even if the response timestamp had no error whatsoever, when it is compared with the stimulus presentation time, the response latency would be wrong due to errors in measures stimulus presentation time. Based on this large set of problems with collecting accurate response latency data, it is my firm belief that the only way to accurately measure response latency is with a button box that measures actual stimulus onset time with a light or sound sensor and also measures the time of a button press or other response. If you don't use such a system, the expectation is that you simply allow any error in response latencies to be dealt with statistically. Typically, any systematic error in response times will be subtracted out when conditions are compared with one another. Any random error will simply slightly inflate the estimated variance, but probably not to any meaningful extent.

If you would like to learn more about the internals of how input is handled in CX, you can see how GLFW and open-Framworks manage input by examining the source code in the respective repositories.

*Technically, on Windows the messages that are given to a program do have a timestamp. However, the documentation doesn't actually say what the timestamp represents. My searching turns up the suggestion that it is a timestamp in milliseconds from system boot, but that the timestamp is set using the GetTickCount function, which typically has worse than 10 ms precision. This makes the timestamp attached to the message of very little value. See this page for documentation of what information comes with a Windows message: http://msdn.microsoft.com/en-us/library/windows/desktop/ms644958%28v=vs.85%29.aspx. The only page on which I actually found a definition of what the time member stores is this page http://msdn.-microsoft.com/en-us/library/aa929818.aspx, which gives information pertaining to Windows Mobile 6.5, which is an obsolete smartphone operating system.

Stimulus Timing

5 license

The code in this repository is available under the MIT License (https://secure.wikimedia.org/wikipedia/en/wiki/-Mit_license).

Copyright (c) 2014 Kyle Hardman

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

6 Module Index

6.1 Modules

Here is a list of all modules:

Data	12
Entry Point	13
Error Logging	14
Input Devices	15
Randomization	16
Sound	17
Timing	18
Utility	19
Video	20

7 Namespace Index

7.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

8 Hierarchical Index		•

	CX	21
	CX::Algo	22
	CX::Draw	24
	CX::Instances	26
	CX::Private	26
	CX::Synth	27
	CX::Util	28
8	Hierarchical Index	
8.1	Class Hierarchy	
Th	is inheritance list is sorted roughly, but not completely, alphabetically:	
	CX::CX_SoundStream::Configuration	37
	CX::CX_SlidePresenter::Configuration	38
	CX::CX_Clock	39
	CX::Util::CX_CoordinateConverter	41
	CX::CX_DataFrame	44
	CX::CX_DataFrameCell	51
	CX::CX_DataFrameColumn	55
	CX::CX_DataFrameRow	55
	CX::Util::CX_DegreeToPixelConverter	56
	CX::CX_Display	57
	CX::CX_InputManager	61
	CX::CX_Joystick	62
	CX::CX_Keyboard	63
	CX::Util::CX_LengthToPixelConverter	65
	CX::CX_Logger	66
	CX::CX_Mouse	68
	CX::CX_RandomNumberGenerator	69
	CX::CX SlidePresenter	75

CX::CX_SoundObject	80
CX::CX_SoundObjectPlayer	87
CX::CX_SoundObjectRecorder	89
CX::CX_SoundStream	90
CX::Util::CX_TrialController	95
CX::CX_Mouse::Event	97
CX::CX_Joystick::Event	98
CX::CX_Keyboard::Event	99
CX::CX_SlidePresenter::FinalSlideFunctionArgs	100
CX::CX_SoundStream::InputEventArgs	102
CX::Synth::ModuleBase	103
CX::Synth::Adder	32
CX::Synth::AdditiveSynth	33
CX::Synth::Clamper	36
CX::Synth::Envelope	97
CX::Synth::FIRFilter	101
CX::Synth::Mixer	102
CX::Synth::Multiplier	104
CX::Synth::Oscillator	105
CX::Synth::RCFilter	107
CX::Synth::RecursiveFilter	108
CX::Synth::SoundObjectInput	111
CX::Synth::SoundObjectOutput	112
CX::Synth::Splitter	112
CX::Synth::StreamOutput	114
CX::CX_SoundStream::OutputEventArgs	106
CX::CX_SlidePresenter::PresentationErrorInfo	107
CX::CX_SlidePresenter::Slide	109
CX::CX_SlidePresenter::SlideTimingInfo	110
CX::Synth::StereoSoundObjectOutput	113

9 Class Index 9

	CX::Synth::StereoStreamOutput	114
9	Class Index	
9.1	Class List	
He	re are the classes, structs, unions and interfaces with brief descriptions:	
	CX::Synth::Adder	32
	CX::Synth::AdditiveSynth	33
	CX::Synth::Clamper	36
	CX::CX_SoundStream::Configuration	37
	CX::CX_SlidePresenter::Configuration	38
	CX::CX_Clock	39
	CX::Util::CX_CoordinateConverter	41
	CX::CX_DataFrame	44
	CX::CX_DataFrameCell	51
	CX::CX_DataFrameColumn	55
	CX::CX_DataFrameRow	55
	CX::Util::CX_DegreeToPixelConverter	56
	CX::CX_Display	57
	CX::CX_InputManager	61
	CX::CX_Joystick	62
	CX::CX_Keyboard	63
	CX::Util::CX_LengthToPixelConverter	65
	CX::CX_Logger	66
	CX::CX_Mouse	68
	CX::CX_RandomNumberGenerator	69
	CX::CX_SlidePresenter	75
	CX::CX_SoundObject	80
	CX::CX_SoundObjectPlayer	87
	CX::CX_SoundObjectRecorder	89

CX::CX_SoundStream	90
CX::Util::CX_TrialController	95
CX::Synth::Envelope	97
CX::CX_Mouse::Event	97
CX::CX_Joystick::Event	98
CX::CX_Keyboard::Event	99
CX::CX_SlidePresenter::FinalSlideFunctionArgs	100
CX::Synth::FIRFilter	101
CX::CX_SoundStream::InputEventArgs	102
CX::Synth::Mixer	102
CX::Synth::ModuleBase	103
CX::Synth::Multiplier	104
CX::Synth::Oscillator	105
CX::CX_SoundStream::OutputEventArgs	106
CX::CX_SlidePresenter::PresentationErrorInfo	107
CX::Synth::RCFilter	107
CX::Synth::RecursiveFilter	108
CX::CX_SlidePresenter::Slide	109
CX::CX_SlidePresenter::SlideTimingInfo	110
CX::Synth::SoundObjectInput	111
CX::Synth::SoundObjectOutput	112
CX::Synth::Splitter	112
CX::Synth::StereoSoundObjectOutput	113
CX::Synth::StereoStreamOutput	114
CX::Synth::StreamOutput	114

10 File Index

10.1 File List

Here is a list of all documented files with brief descriptions:

10.1 File List

advancedChangeDetectionTask.cpp	115
basicChangeDetectionTask.cpp	116
CX_Algorithm.h	??
CX_AppWindow.h	??
CX_Clock.h	??
CX_ClockImplementations.h	??
CX_DataFrame.h	??
CX_DataFrame_attempts.h	??
CX_DataFrameCell.h	??
CX_Display.h	??
CX_Draw.h	??
CX_EntryPoint.h	??
CX_Events.h	??
CX_InputManager.h	??
CX_Joystick.h	??
CX_Keyboard.h	??
CX_Logger.h	??
CX_LoggerChannel.h	??
CX_ModularSynth.h	??
CX_Mouse.h	??
CX_Private.h	??
CX_RandomNumberGenerator.h	??
CX_SlidePresenter.h	??
CX_SoundObject.h	??
CX_SoundObjectPlayer.h	??
CX_SoundObjectRecorder.h	??
CX_SoundStream.h	??
CX_TrialController.h	??
CX_TrialController_Class.h	??
CX_UnitConversion.h	??

CX_Utilities.h	??
CX_VideoBufferSwappingThread.h	??
myType.h	??
nBack.cpp	116

11 Module Documentation

11.1 Data

Classes

- class CX::CX_DataFrame
- class CX::CX_DataFrameColumn
- class CX::CX DataFrameRow
- class CX::CX_DataFrameCell

11.1.1 Detailed Description

This module is related to storing experimental data. CX_DataFrame is the most important class in this module.

11.2 Entry Point 13

11.2 Entry Point

Functions

void runExperiment (void)

Variables

- CX_Display CX::Instances::Display
- CX_InputManager CX::Instances::Input
- CX Logger CX::Instances::Log
- CX_RandomNumberGenerator CX::Instances::RNG

11.2.1 Detailed Description

The entry point provides access to a few instances of classes that can be used by user code. It also provides declarations (but not definitions) of a function which the user should define (see runExperiment()).

11.2.2 Function Documentation

```
11.2.2.1 runExperiment (void)
```

The user code should define a function with this name and type signature (takes no arguments and returns nothing). This function will be called once setup is done for CX. When runExperiment returns, the program will exit.

```
void runExperiment (void) {
    //Do your experiment.

return; //Return when done to exit the program. You don't have to explicity return; you can just fall off the end of the function.
    //You can alternately call std::exit() or ofExit() at any point.
}
```

11.2.3 Variable Documentation

11.2.3.1 CX::CX_Display CX::Instances::Display

An instance of CX::CX_Display that is lightly hooked into the CX backend. setup() is called for Display before run-Experiment() is called.

```
11.2.3.2 CX::CX_InputManager CX::Instances::Input
```

An instance of CX_InputManager that is very lightly hooked into the CX backend.

```
11.2.3.3 CX_Logger CX::Instances::Log
```

This is an instance of CX::CX_Logger that is hooked into the CX backend. All log messages generated by CX and openFrameworks go through this instance.

```
11.2.3.4 CX::CX RandomNumberGenerator CX::Instances::RNG
```

An instance of CX_RandomNumberGenerator that is (lightly) hooked into the CX backend.

11.3 Error Logging

Classes

· class CX::CX_Logger

Enumerations

```
    enum CX::CX_LogLevel {
    LOG_ALL, LOG_VERBOSE, LOG_NOTICE, LOG_WARNING,
    LOG_ERROR, LOG_FATAL_ERROR, LOG_NONE }
```

- 11.3.1 Detailed Description
- 11.3.2 Enumeration Type Documentation

```
11.3.2.1 enum CX::CX_LogLevel [strong]
```

Log levels for log messages. Depending on the log level chosen, the name of the level will be printed before the message. Depending on the settings set using level(), levelForConsole(), or levelForFile(), if the log level of a message is below the level set for the module or logging target it will not be printed. For example, if LOG_ERROR is the level for the console and LOG_NOTICE is the level for the module "test", then messages logged to the "test" module will be completely ignored if at verbose level (because of the module setting) and will not be printed to the console if they are below the level of an error (because of the console setting).

11.4 Input Devices 15

11.4 Input Devices

Classes

- class CX::CX_InputManager
- class CX::CX_Joystick
- · class CX::CX_Keyboard
- class CX::CX_Mouse

11.4.1 Detailed Description

There are a number of different classes that together perform the input handling functions of CX. Start by looking at CX::CX_InputManager and the instance of that class that is created for you: CX::Instances::Input.

For interfacing with serial ports, use of Serial (http://www.openframeworks.cc/documentation/communication/of-Serial.html).

See Also

CX::CX_InputManager for the primary interface to input devices.

CX::CX_Keyboard for keyboard specific information.

CX::CX_Mouse for mouse specific information.

CX::CX_Joystick for joystick specific information.

11.5 Randomization

Classes

• class CX::CX_RandomNumberGenerator

11.5.1 Detailed Description

This module provides a class that is used for random number generation.

11.6 Sound 17

11.6 Sound

Classes

- class CX::CX_SoundObjectRecorder
- class CX::CX_SoundObject
- class CX::CX_SoundObjectPlayer
- class CX::CX_SoundStream

11.6.1 Detailed Description

11.7 Timing

Classes

class CX::CX_Clock

Variables

• CX_Clock CX::Instances::Clock

11.7.1 Detailed Description

This module provides methods for timestamping events in experiments.

11.7.2 Variable Documentation

11.7.2.1 CX_Clock CX::Instances::Clock

An instance of CX::CX_Clock that is hooked into the CX backend. Anything in CX that requires timing information uses this instance. You should use this instance in your code and not make your own instance of CX_Clock. You should never need another instance. You should never use another instance, as the experiment start times will not agree between instances.

11.8 Utility 19

11.8 Utility

Namespaces

• CX::Util

Classes

- class CX::Util::CX_TrialController
- class CX::Util::CX_DegreeToPixelConverter
- class CX::Util::CX_LengthToPixelConverter
- class CX::Util::CX_CoordinateConverter

11.8.1 Detailed Description

11.9 Video

Namespaces

• CX::Draw

Classes

- class CX::CX_Display
- class CX::CX_SlidePresenter

11.9.1 Detailed Description

This module is related to creating and presenting visual stimuli. Mostly, it is responsible for controlling presentation timing of stimuli rather than actually creating the stimuli.

Almost all of the actual drawing of stimuli is done using openFrameworks functions. A lot of the common functions can be found in ofGraphics.h (http://www.openframeworks.cc/documentation/graphics/of-Graphics.html), but there are a lot of other ways to draw stimuli: see the graphics and 3d sections if this page: http://www.openframeworks.cc/documentation/.

12 Namespace Documentation

12.1 CX Namespace Reference

Namespaces

- Algo
- Draw
- Instances
- Private
- Synth
- Util

Classes

- class CX Clock
- class CX DataFrame
- class CX_DataFrameColumn
- class CX DataFrameRow
- class CX_DataFrameCell
- class CX_Display
- class CX_InputManager
- class CX Joystick
- · class CX_Keyboard
- class CX Logger
- class CX Mouse
- class CX RandomNumberGenerator
- class CX SlidePresenter
- class CX_SoundObject
- class CX_SoundObjectPlayer
- class CX_SoundObjectRecorder
- class CX_SoundStream

Typedefs

- typedef long long CX_Micros
- typedef int64_t CX_RandomInt_t
- typedef

CX_SoundStream::Configuration CX_SoundObjectPlayerConfiguration_t

This is typedef'ed to CX::CX_SoundStream::Configuration.

Enumerations

- enum CX_LogLevel {
 LOG_ALL, LOG_VERBOSE, LOG_NOTICE, LOG_WARNING,
 LOG_ERROR, LOG_FATAL_ERROR, LOG_NONE }
- enum CX_MouseButtons: int { LEFT_MOUSE = OF_MOUSE_BUTTON_LEFT, MIDDLE_MOUSE = OF_MOUSE_BUTTON_RIGHT }

Functions

- std::ostream & operator<< (std::ostream &os, const CX DataFrameCell &cell)
- std::ostream & operator<< (std::ostream &os, const CX Joystick::Event &ev)
- std::istream & operator>> (std::istream &is, CX_Joystick::Event &ev)
- std::ostream & operator<< (std::ostream &os, const CX Keyboard::Event &ev)
- std::istream & operator>> (std::istream &is, CX_Keyboard::Event &ev)
- std::ostream & operator<< (std::ostream &os, const CX_Mouse::Event &ev)
- std::istream & operator>> (std::istream &is, CX_Mouse::Event &ev)

12.1.1 Detailed Description

This namespace contains all of the symbols related to CX.

12.2 CX::Algo Namespace Reference

Functions

- template<typename T >
 std::vector< T > generateSeparatedValues (int count, double minDistance, std::function< double(T, T)>
 distanceFunction, std::function< T(void)> randomDeviate, int maxSequentialFailures=200)
- template<typename T >
 std::vector< std::vector< T > > fullyCross (std::vector< std::vector< T > > factors)

12.2.1 Detailed Description

This namespace contains a few complex algorithms that can be difficult to properly implement.

12.2.2 Function Documentation

```
12.2.2.1 template < typename T > std::vector < T > > CX::Algo::fullyCross ( std::vector < std::vector < T > > factors )
```

This function fully crosses the levels of the factors of a design. For example, for a 2X3 design, it would give you all 6 combinations of the levels of the design.

Parameters

```
factors A vector of factors, each factor being a vector containing all the levels of that factor.
```

Returns

A vector of crossed factor levels. It's length is equal to the product of the levels of the factors. The length of each "row" is equal to the number of factors.

Example use:

```
std::vector< std::vector<int> > levels(2); //Two factors
levels[0].push_back(1); //The first factor has two levels (1 and 2)
levels[0].push_back(2);
levels[1].push_back(3); //The second factor has three levels (3, 4, and 5)
levels[1].push_back(4);
levels[1].push_back(5);
auto crossed = fullyCross(levels);
```

crossed should contain a vector with six subvectors with the contents:

```
{ {1,3}, {1,4}, {1,5}, {2,3}, {2,4}, {2,5} }
where

crossed[3][0] == 2
crossed[3][1] == 3
crossed[0][1] == 3
```

12.2.2.2 template < typename T > std::vector < T > CX::Algo::generateSeparatedValues (int *count*, double *minDistance*, std::function < double(T, T)> distanceFunction, std::function < T(void)> randomDeviate, int maxSequentialFailures = 200)

This poorly-named algorithm is designed to deal with the situation in which a number of random values must be generated that are each at least some distance from every other random value. This is a very generic implementation of this algorithm. It works by taking pointers to two functions that work on whatever type of data you are using. The first function is a distance function: it returns the distance between two values of the type. The second function generates random values of the type.

Template Parameters

< <i>T</i> >	The type of data you are working with.

Parameters

count	The number of values you want to be generated.
minDistance	The minimum distance between any two values. This will be compared to the result of distance-
	Function.
distanceFunction	A function that computes the distance, in whatever units you want, between two values of type T.
randomDeviate	A function that generates random values of type T.
maxSequential-	The maximum number of times in a row that a newly-generated value is less than minDistance
Failures	from at least one other value. This essentially makes sure that if it is not possible to generate a
	random value that is at least some distance from the others, the algorithm will terminate.

Returns

A vector of values. If the function terminated prematurely due to maxSequentialFailures being reached, the returned vector will have 0 elements.

```
//This example function generates locCount points with both x and y values bounded by minimumValues and
    maximumValues that
//are at least minDistance pixels from each other.
std::vector<ofPoint> getObjectLocations(int locCount, double minDistance, ofPoint minimumValues, ofPoint
    maximumValues) {
    auto pointDistance = [] (ofPoint a, ofPoint b) {
        return sqrt(pow(a.x - b.x, 2) + pow(a.y - b.y, 2));
    };

    auto randomPoint = [&]() {
        ofPoint rval;
        rval.x = RNG.randomInt(minimumValues.x, maximumValues.x);
        rval.y = RNG.randomInt(minimumValues.y, maximumValues.y);
        return rval;
    };

    return CX::Algo::generateSeparatedValues<ofPoint>(locCount, minDistance, pointDistance, randomPoint,
        1000);
}

//Call of example function
vector<ofPoint> v = getObjectLocations(5, 50, ofPoint(0, 0), ofPoint(400, 400));
```

12.3 CX::Draw Namespace Reference

Functions

- ofPath squircleToPath (double radius, double amount=0.9)
- ofPath starToPath (int numberOfPoints, double innerRadius, double outerRadius)
- void star (ofPoint center, int numberOfPoints, float innerRadius, float outerRadius, ofColor lineColor, ofColor fill-Color, float lineWidth=1, float rotationDeg=0)
- void centeredString (int x, int y, std::string s, ofTrueTypeFont &font)
- void centeredString (ofPoint center, std::string s, ofTrueTypeFont &font)
- ofPixels greyscalePattern (const CX PatternProperties t &patternProperties)
- ofPixels gaborToPixels (const CX_GaborProperties_t &properties)
- ofTexture gaborToTexture (const CX_GaborProperties_t &properties)
- void **gabor** (int x, int y, const CX_GaborProperties_t &properties)

12.3.1 Detailed Description

This namespace contains functions for drawing certain complex stimuli.

12.3.2 Function Documentation

12.3.2.1 void CX::Draw::centeredString (int x, int y, std::string s, ofTrueTypeFont & font)

Equivalent to a call to CX::Draw::centeredString(ofPoint(x, y), s, font).

12.3.2.2 void CX::Draw::centeredString (ofPoint center, std::string s, ofTrueTypeFont & font)

Draws a string centered on a given location using the given font. Strings are normally drawn such that the x coordinate gives the left edge of the string and the y coordinate gives the line above which the letters will be drawn, where some characters (like y or g) can descend below the line.

Parameters

center	The coordinates of the center of the string.
s	The string to draw.
font	A font that has already been prepared for use.

12.3.2.3 of Path CX::Draw::squircleToPath (double radius, double amount = 0.9)

This function draws an approximation of a squircle (http://en.wikipedia.org/wiki/Squircle) using Bezier curves. The squircle will be centered on (0,0) in the ofPath.

Parameters

radius	The radius of the largest circle that can be enclosed in the squircle.
amount	The "squircliness" of the squircle. The default (0.9) seems like a pretty good amount for a good
	approximation of a squircle, but different amounts can give different sorts of shapes.

Returns

An ofPath containing the squircle.

12.3.2.4 void CX::Draw::star (ofPoint center, int numberOfPoints, float innerRadius, float outerRadius, ofColor lineColor, ofColor fillColor, float lineWidth = 1, float rotationDeg = 0)

This draws an N-pointed star.

Parameters

center	The point at the center of the star.
numberOfPoints	The number of points in the star.
innerRadius	The distance from the center of the star to where the inner points of the star hit.
outerRadius	The distance from the center of the star to the outer points of the star.
lineColor	The color of the lines going around the edge of the star.
fillColor	The color used to fill in the center of the star.
lineWidth	The width of the lines.
rotationDeg	The number of degrees to rotate the star. 0 degrees has one point of the star pointing up. Positive
	values rotate the star counter-clockwise.

Returns

An ofPath containing the star.

12.3.2.5 of Path CX::Draw::starToPath (int numberOfPoints, double innerRadius, double outerRadius)

This draws an N-pointed star to an ofPath. The star will be centered on (0,0) in the ofPath.

Parameters

numberOfPoints	The number of points in the star.
innerRadius	The distance from the center of the star at which the inner points of the star hit.
outerRadius	The distance from the center of the star to the outer points of the star.

Returns

An ofPath containing the star.

12.4 CX::Instances Namespace Reference

Variables

- CX_Clock Clock
- CX Display Display
- CX InputManager Input
- CX_Logger Log
- CX_RandomNumberGenerator RNG

12.4.1 Detailed Description

This namespace contains instances of some classes that are fundamental to the functioning of CX.

12.5 CX::Private Namespace Reference

Functions

- void **glfwErrorCallback** (int code, const char *message)
- CX_Events & getEvents (void)
- CX_GLVersion getOpenGLVersion (void)
- CX_GLVersion getGLSLVersion (void)

- bool glFenceSyncSupported (void)
- bool glVersionAtLeast (int desiredMajor, int desiredMinor, int desiredRelease=0)
- int glCompareVersions (CX GLVersion a, CX GLVersion b)
- CX_GLVersion getGLSLVersionFromGLVersion (CX_GLVersion glVersion)

Variables

- GLFWwindow * glfwContext = NULL
- ofPtr< CX AppWindow > window

12.5.1 Detailed Description

This namespace contains symbols that may be visible in user code but which should not be used by user code.

12.6 CX::Synth Namespace Reference

Classes

- class ModuleBase
- · class AdditiveSynth
- · class Adder
- · class Clamper
- class Envelope
- · class Mixer
- class Multiplier
- · class Splitter
- class SoundObjectInput
- · class Oscillator
- class StreamOutput
- · class StereoStreamOutput
- · class SoundObjectOutput
- class StereoSoundObjectOutput
- class FIRFilter
- class RecursiveFilter
- · class RCFilter

Functions

- double **sinc** (double x)
- double relativeFrequency (double f, double semitoneDifference)

12.6.1 Detailed Description

This namespace contains a number of classes that can be combined together to form a modular synth that can be used to generate sound stimuli.

12.7 CX::Util Namespace Reference

Classes

- class CX TrialController
- class CX_DegreeToPixelConverter
- class CX_LengthToPixelConverter
- class CX_CoordinateConverter

Enumerations

enum CX_RoundingConfiguration { ROUND_TO_NEAREST, ROUND_UP, ROUND_DOWN, ROUND_TOW-ARD_ZERO }

Functions

- float degreesToPixels (float degrees, float pixelsPerUnit, float viewingDistance)
- float pixelsToDegrees (float pixels, float pixelsPerUnit, float viewingDistance)
- bool checkOFVersion (int versionMajor, int versionMinor, int versionPatch)
- int getSampleCount (void)
- template<typename T >
 - std::vector< T > arrayToVector (T arr[], unsigned int arraySize)
- template<typename T >
 - std::vector< T > sequence (T start, T end, T stepSize)
- template<typename T >
 - std::vector< T > sequenceSteps (T start, unsigned int steps, T stepSize)
- template<typename T >
 - std::vector< T > sequenceAlong (T start, T end, unsigned int steps)
- template<typename T >
- std::vector< T > intVector (T start, T end)
- template<typename T >
 - std::vector< T > repeat (T value, unsigned int times)
- template<typename T >
 - std::vector< T > repeat (std::vector< T > values, unsigned int times, unsigned int each=1)
- $\bullet \ \ template {<} typename \ T >$
 - t=1 std::vector t>t=1 std::vector t>t=1
- template<typename T >
 - std::string vectorToString (std::vector< T > values, std::string delimiter=",", int significantDigits=8)
- bool writeToFile (std::string filename, std::string data, bool append=true)
- double round (double d, int roundingPower, CX_RoundingConfiguration c)
- template<typename T >
 - T clamp (T val, T minimum, T maximum)

12.7.1 Detailed Description

This namespace contains a variety of utility functions.

12.7.2 Function Documentation

12.7.2.1 template < typename T > std::vector < T > CX::Util::arrayToVector (T arr[], unsigned int arraySize)

Copies arraySize elements of an array of T to a vector<T>.

Template Parameters

< <i>T</i> >	The type of the array. Is often inferred by the compiler.

Parameters

arr	The array of data to put into the vector.
arraySize	The length of the array, or the number of elements to copy from the array if not all of the elements
	are wanted.

Returns

The elements in a vector.

12.7.2.2 bool CX::Util::checkOFVersion (int versionMajor, int versionMinor, int versionPatch)

Checks that the version of oF that is used during compilation matches the requested version. If the desired version was 0.7.1, simply input (0, 7, 1) as the arguments. A warning will be logged if the versions don't match.

Returns

True if the versions match, false otherwise.

12.7.2.3 template < typename T > T CX::Util::clamp (T val, T minimum, T maximum)

Clamps a value (i.e. forces the value to be between two bounds). If the value is outside of the bounds, it is set to be equal to the nearest bound.

Parameters

val	The value to clamp.
minimum	The lower bound. Must be less than or equal to maximum.
maximum	The upper bound. Must be greater than or equal to minimum.

Returns

The clamped value.

12.7.2.4 float CX::Util::degreesToPixels (float degrees, float pixelsPerUnit, float viewingDistance)

Returns the number of pixels needed to subtend deg degrees of visual angle. You might want to round this if you want to align to pixel boundaries. However, if you are antialiasing your stimuli you might want to use floating point values to get precise subpixel rendering.

Parameters

deg	Number of degrees.

Returns

The number of pixels needed.

12.7.2.5 template<typename T > std::vector< T > CX::Util::intVector (T start, T end)

Creates a vector of integers going from start to end. start may be greater than end, in which case the returned values will be in descending order. This is similar to using CX::sequence, but the step size is fixed to 1 and it works properly when trying to create a descending sequence of unsigned integers.

Returns

A vector of the values int the sequence.

12.7.2.6 float CX::Util::pixelsToDegrees (float pixels, float pixelsPerUnit, float viewingDistance)

The inverse of CX::Util::degreesToPixels().

12.7.2.7 template < typename T > std::vector < T > CX::Util::repeat (T value, unsigned int times)

Repeats value "times" times.

Parameters

value	The value to be repeated.
times	The number of times to repeat the value.

Returns

A vector containing times copies of the repeated value.

12.7.2.8 template < typename T > std::vector< T > CX::Util::repeat (std::vector< T > values, unsigned int times, unsigned int each = 1)

Repeats the elements of values. Each element of values is repeated "each" times and then the process of repeating the elements is repeated "times" times.

Parameters

values	Vector of values to be repeated.
times	The number of times the process should be performed.
each	Number of times each element of values should be repeated.

Returns

A vector of the repeated values.

12.7.2.9 template < typename T > std::vector < T > CX::Util::repeat (std::vector < T > values, std::vector < unsigned int > each, unsigned int times = 1)

Repeats the elements of values. Each element of values is repeated "each" times and then the process of repeating the elements is repeated "times" times.

Parameters

values	Vector of values to be repeated.
each	Number of times each element of values should be repeated. Must be the same length as values.
	If not, an error is logged and an empty vector is returned.
times	The number of times the process should be performed.

Returns

A vector of the repeated values.

12.7.2.10 double CX::Util::round (double d, int roundingPower, CX_RoundingConfiguration c)

Rounds the given double to the given power of 10.

Parameters

d	The number to be rounded.
roundingPower	The power of 10 to round d to. For example, if roundingPower is 0, d is rounded to the one's
	place ($10^{\circ}0 == 1$). If roundingPower is -3, d is rounded to the thousandth's place ($10^{\circ}-3 = .001$).
	If roundingPower is 1, d is rounded to the ten's place.
С	The type of rounding to do, from the CX::Util::CX_RoundingConfiguration enum. You can round
	up, down, to nearest, and toward zero.

Returns

The rounded value.

12.7.2.11 template < typename T > std::vector < T > CX::Util::sequence (T start, T end, T stepSize)

Creates a sequence of numbers from start to end by steps of size stepSize. start may be geater than end, but only if stepSize is less than 0. If start is less than end, stepSize must be greater than 0.

Example call: sequence<double>(1, 3.3, 2) results in a vector containing {1, 3}

Parameters

start	The start of the sequence. You are guaranteed to get this value in the sequence.
end	The number past which the sequence should end. You are not guaranteed to get this value.
stepSize	A nonzero number.

Returns

A vector containing the sequence.

12.7.2.12 template<typename T > std::vector< T > CX::Util::sequenceAlong (T start, T end, unsigned int outputLength)

Creates a sequence from start to end, where the size of each step is chosen so that the length of the sequence if equal to outputLength.

Parameters

start	The value at which to start the sequence.
end	The value to which to end the sequence.
outputLength	The number of elements in the returned sequence.

Returns

A vector containing the sequence.

12.7.2.13 template < typename T > std::vector < T > CX::Util::sequenceSteps (T start, unsigned int steps, T stepSize)

Make a sequence starting from start and taking steps steps of stepSize.

sequenceSteps(1.5, 4, 2.5);

Creates the sequence $\{1.5, 4, 6.5, 9, 11.5\}$

Parameters

start	Value from which to start.
steps	The number of steps to take.
stepSize	The size of each step.

Returns

A vector containing the sequence.

12.7.2.14 template < typename T > std::string CX::Util::vectorToString (std::vector < T > values, std::string delimiter = ", ", int significantDigits = 8)

This function converts a vector of values to a string representation of the values.

Parameters

values	The vector of values to convert.
delimiter	A string that is used to separate the elements of value in the final string.
significantDigits	Only for floating point types. The number of significant digits in the value.

Returns

A string containing a representation of the vector of values.

12.7.2.15 bool CX::Util::writeToFile (std::string filename, std::string data, bool append = true)

Writes data to a file, either appending the data to an existing file or creating a new file, overwriting any existing file with the given filename.

Parameters

filename	Name of the file to write to. If it is a relative file name, it will be placed relative the the data
	directory.
data	The data to write
append	If true, data will be appended to an existing file, if it exists. If append is false, any existing file will
	be overwritten and a warning will be logged. If no file exists, a new one will be created.

Returns

True if an error was encountered while writing the file, true otherwise. If there was an error, an error message will be logged.

13 Class Documentation

13.1 CX::Synth::Adder Class Reference

#include <CX_ModularSynth.h>

Inherits CX::Synth::ModuleBase.

Public Member Functions

• double getNextSample (void) override

Public Attributes

ModuleParameter amount

Additional Inherited Members

13.1.1 Detailed Description

This class simply takes an input and adds an amount to it. The amount can be negative, in which case this class is a subtracter.

13.1.2 Member Function Documentation

```
13.1.2.1 double Adder::getNextSample(void) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- CX_ModularSynth.h
- CX ModularSynth.cpp

13.2 CX::Synth::AdditiveSynth Class Reference

```
#include <CX_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Types

- enum HarmonicSeriesType { HS_MULTIPLE, HS_SEMITONE, HS_USER_FUNCTION }
- enum HarmonicAmplitudeType { SINE, SQUARE, SAW, TRIANGLE }
- typedef float wavePos_t
- · typedef float amplitude_t

Public Member Functions

- void configure (unsigned int harmonicCount, HarmonicSeriesType hs, HarmonicAmplitudeType aType)
- void setFundamentalFrequency (double f)
- void setStandardHarmonicSeries (unsigned int harmonicCount)
- void setHarmonicSeries (unsigned int harmonicCount, HarmonicSeriesType type, double controlParameter)
- void setHarmonicSeries (unsigned int harmonicCount, std::function< double(unsigned int)> userFunction)
- void setAmplitudes (HarmonicAmplitudeType type)
- void setAmplitudes (HarmonicAmplitudeType t1, HarmonicAmplitudeType t2, double mixture)
- void setAmplitudes (std::vector< amplitude t > amps)
- std::vector< amplitude t > calculateAmplitudes (HarmonicAmplitudeType type, unsigned int count)
- void pruneLowAmplitudeHarmonics (double tol)
- double getNextSample (void) override

Additional Inherited Members

13.2.1 Detailed Description

This class is an implementation of an additive synthesizer. Additive synthesizers are essentially an inverse fourier transform. You specify at which frequencies you want to have a sine wave and the amplitudes of those waves, and they are combined together into a single waveform.

The frequencies are referred to as harmonics, due to the fact that typical audio applications of additive synths use the standard harmonic series ($f(i) = f_{\text{the fundamental}} * i$). However, setting the harmonics to values not found in the standard harmonic series can result in really unusual and interesting sounds.

13.2.2 Member Function Documentation

13.2.2.1 double AdditiveSynth::getNextSample (void) [override], [virtual]

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

13.2.2.2 void AdditiveSynth::pruneLowAmplitudeHarmonics (double tol)

This function removes all harmonics that have an amplitude that is less than or equal to a tolerance times the amplitude of the frequency with the greatest absolute amplitude.

The result of this pruning is that the synthesizer will be more computationally efficient but provide a possibly worse approximation of the desired waveform.

Parameters

tol	tol is interpreted differently depending on its value. If tol is greater than or equal to 0, it is
	treated as a proportion of the amplitude of the frequency with the greatest amplitude. If tol is
	less than 0, it is treated as the difference in decibels between the frequency with the greatest
	amplitude and the tolerance.

Note

Because harmonics with an amplitude equal to the tolerance times an amplitude, setting tolerance to 0 will remove harmonics with 0 amplitude, but no others.

13.2.2.3 void AdditiveSynth::setAmplitudes (HarmonicAmplitudeType type)

This function sets the amplitudes of the harmonics based on the chosen type. The resulting waveform will only be correct if the harmonic series is the standard harmonic series (see setStandardHarmonicSeries()).

Parameters

type	The type of wave calculate amplitudes for.

13.2.2.4 void AdditiveSynth::setAmplitudes (HarmonicAmplitudeType t1, HarmonicAmplitudeType t2, double mixture)

This function sets the amplitudes of the harmonics based on a mixture of the chosen types. The resulting waveform will only be correct if the harmonic series is the standard harmonic series (see setStandardHarmonicSeries()). This is a convenient way to morph between waveforms.

13.2.2.5 void AdditiveSynth::setAmplitudes (std::vector< amplitude_t > amps)

This function sets the amplitudes of the harmonics to arbitrary values as specified in amps.

Parameters

amps	The amplitudes of the harmonics. If this vector does not contain as many values as there are
	harmonics, the unspecified amplitudes will be set to 0.

13.2.2.6 void AdditiveSynth::setHarmonicSeries (unsigned int *harmonicCount*, HarmonicSeriesType *type*, double *controlParameter*)

Parameters

type	The type of harmonic series to generate. Can be either HS_MULTIPLE or HS_SEMITONE.
	For HS_MULTIPLE, each harmonic's frequency will be some multiple of the fundamental fre-
	quency, depending on the harmonic number and controlParameter. For HS_SEMITONE, each
	harmonic's frequency will be some number of semitones above the previous frequency, based
	on controlParameter (specifying the number of semitones).
controlParameter	If type == HS_MULTIPLE, the frequency for harmonic i will be i * controlParameter, where the
	fundamental gives the value 1 for i. If type == HS_SEMITONE, the frequency for harmonic
	i will be pow(2, (i - 1) * controlParameter/12), where the fundamental gives
	the value 1 for i.

Note

If type == HS_MULTIPLE and controlParameter == 1, then the standard harmonic series will be generated.

If type == HS_SEMITONE, controlParameter does not need to be an integer.

13.2.2.7 void AdditiveSynth::setHarmonicSeries (unsigned int *harmonicCount,* std::function < double(unsigned int) > userFunction)

This function calculates the harmonic series from a function supplied by the user.

Parameters

harmonicCount	The number of harmonics to generate.
userFunction	The user function takes an integer representing the harmonic number, where the fundamental
	has the value 1, and returns the frequency that should be used for that harmonic.

13.2.2.8 void AdditiveSynth::setStandardHarmonicSeries (unsigned int harmonicCount)

The standard harmonic series begins with the fundamental frequency f1 and each seccuessive harmonic has a frequency equal to f1 * n, where n is the harmonic number for the harmonic. This is the natural harmonic series, one that occurs, e.g., in a vibrating string.

The documentation for this class was generated from the following files:

- · CX_ModularSynth.h
- CX ModularSynth.cpp

13.3 CX::Synth::Clamper Class Reference

#include <CX_ModularSynth.h>

Inherits CX::Synth::ModuleBase.

Public Member Functions

double getNextSample (void) override

Public Attributes

- · ModuleParameter low
- · ModuleParameter high

Additional Inherited Members

13.3.1 Detailed Description

This class clamps inputs to be in the interval [low, high], where low and high are the members of this class.

13.3.2 Member Function Documentation

```
13.3.2.1 double Clamper::getNextSample (void ) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- CX_ModularSynth.h
- CX_ModularSynth.cpp

13.4 CX::CX_SoundStream::Configuration Struct Reference

```
#include <CX_SoundStream.h>
```

Public Attributes

· int inputChannels

The number of input (e.g. microphone) channels to use. If 0, no input will be used.

· int outputChannels

The number of output channels to use. Currently only stereo and mono are well-supported. If 0, no output will be used.

- · int sampleRate
- · unsigned int bufferSize
- RtAudio::Api api
- RtAudio::StreamOptions streamOptions
- · int inputDeviceId

The ID of the desired input device. A value of -1 will cause the system default input device to be used.

· int outputDeviceId

The ID of the desired output device. A value of -1 will cause the system default output device to be used.

13.4.1 Detailed Description

This struct controls the configuration of the CX SoundStream.

13.4.2 Member Data Documentation

13.4.2.1 RtAudio::Api CX::CX_SoundStream::Configuration::api

This argument depends on your operating system. Using RtAudio::Api::UNSPECIFIED will attempt to pick a working API from those that are available on your system. The API means the type of software interface to use. For example, on Windows, you can choose from Windows Direct Sound (DS) and ASIO. ASIO is commonly used with audio recording equipment because it has lower latency whereas DS is more of a consumer-grade interface. The choice of API does not affect how you use this class, but it may affect the performance of sound playback.

See http://www.music.mcgill.ca/~gary/rtaudio/classRtAudio.html#ac9b6f625da88249d08a8409a9db for a listing of the APIs. See http://www.music.mcgill.ca/~gary/rtaudio/classRtAudio.-html#afd0bfa26deae9804e18faff59d0273d9 for the default ordering of the APIs if RtAudio::Api::UNSPEC-IFIFD is used.

13.4.2.2 unsigned int CX::CX_SoundStream::Configuration::bufferSize

The size of the audio data buffer to use. A larger buffer size means more latency but also a greater potential for audio glitches (clicks and pops). Buffer size is per channel (i.e. if there are two channels and buffer size is set to 256, the actual buffer size will be 512 samples). Defaults to 4096 samples.

13.4.2.3 int CX::CX_SoundStream::Configuration::sampleRate

The requested sample rate for the input and output channels. If, for the selected device(s), this sample cannot be used, the nearest greater sample rate will be chosen. If there is no greater sample rate, the next lower sample rate will be used.

13.4.2.4 RtAudio::StreamOptions CX::CX_SoundStream::Configuration::streamOptions

See http://www.music.mcgill.ca/~gary/rtaudio/structRtAudio_1_1StreamOptions.html for more information.

flags must not include RTAUDIO_NONINTERLEAVED: The audio data used by CX is interleaved.

The documentation for this struct was generated from the following file:

· CX SoundStream.h

13.5 CX::CX_SlidePresenter::Configuration Struct Reference

#include <CX_SlidePresenter.h>

Public Types

 enum SwappingMode { SINGLE_CORE_BLOCKING_SWAPS, SINGLE_CORE_THREADED_SWAPS, MUL-TI CORE }

Public Attributes

CX Display * display

A pointer to the display to use.

std::function< void(CX SlidePresenter::FinalSlideFunctionArgs &)> finalSlideCallback

A pointer to a user function that will be called as soon as the final slide is presented.

- CX SlidePresenter::ErrorMode errorMode
- bool deallocateCompletedSlides

If true, once a slide has been presented, its framebuffer will be deallocated to conserve memory.

CX_Micros preSwapCPUHoggingDuration

Only used if swappingMode is a single core mode. The amount of time, before a slide is swapped from the back buffer to the front buffer, that the CPU is put into a spinloop waiting for the buffers to swap.

• enum

CX::CX_SlidePresenter::Configuration::SwappingMode swappingMode

13.5.1 Detailed Description

This struct is used for configuring a CX_SlidePresenter.

The documentation for this struct was generated from the following file:

• CX_SlidePresenter.h

13.6 CX::CX Clock Class Reference

```
#include <CX_Clock.h>
```

Public Types

 typedef std::chrono::high resolution clock CX InternalClockType

Public Member Functions

- void precisionTest (unsigned int iterations)
- CX_Micros getTime (void)
- CX Micros getSystemTime (void)
- CX_Micros getExperimentStartTime (void)
- std::string getExperimentStartDateTimeString (std::string format="%Y-%b-%e %h-%M-%S %a")

Static Public Member Functions

static std::string getDateTimeString (std::string format="%Y-%b-%e %h-%M-%S %a")

13.6.1 Detailed Description

This class is responsible for getting timestamps for anything requiring timestamps. The way to get timing information is the function getTime(). It returns the current time relative to the start of the experiment in microseconds (on most systems, see getTickPeriod() to check the actual precision).

An instance of this class is preinstantiated for you. See CX::Instances::Clock.

- 13.6.2 Member Function Documentation
- 13.6.2.1 std::string CX_Clock::getDateTimeString (std::string format = "%Y-%b-%e %h-%M-%S %a") [static]

This function returns a string containing the local time encoded according to some format.

Parameters

format	See http://pocoproject.org/docs/Poco.DateTimeFormatter.html#4684
	for documentation of the format. E.g. "%Y/%m/%d %H:%M:%S" gives "year/month/day 24Hour-
	Clock:minute:second" with some zero-padding for most things. The default "%Y-%b-%e %h-
	%M-%S %a" is "yearWithCentury-abbreviatedMonthName-nonZeroPaddedDay 12HourClock-
	minuteZeroPadded-secondZeroPadded am/pm".

13.6.2.2 std::string CX Clock::getExperimentStartDateTimeString (std::string format = "%Y-%b-%e %h-%M-%S %a")

Get a string representing the date/time of the start of the experiment encoded according to a format.

Parameters

format | See getDateTimeString() for the definition of the format.

13.6.2.3 CX_Micros CX_Clock::getExperimentStartTime (void)

Get the start time of the experiment in system time. The returned value can be compared with the result of getSystem-Time().

13.6.2.4 CX_Micros CX_Clock::getSystemTime (void)

This function returns the current system time in microseconds.

This cannot be converted to time/day in any meaningful way. Use getDateTimeString() for that.

Returns

A time value that can be compared to the result of other calls to this function and to getExperimentStartTime().

13.6.2.5 CX_Micros CX_Clock::getTime (void)

This function returns the current time relative to the start of the experiment in microseconds. The start of the experiment is defined by default as when the CX_Clock instance named Clock (instantiated in this file) is constructed (typically the beginning of program execution).

13.6.2.6 void CX_Clock::precisionTest (unsigned int iterations)

This function tests the precision of the clock used by CX. The results are computer-specific. If the precision of the clock is worse than microsecond accuracy, a warning is logged including information about the actual precision of the clock.

Depending on the number of iterations, this function may be considered blocking. See Blocking Code.

Parameters

iterations Number of time duration samples to take. More iterations should give a better estimate.

The documentation for this class was generated from the following files:

- · CX_Clock.h
- CX Clock.cpp

13.7 CX::Util::CX_CoordinateConverter Class Reference

#include <CX_UnitConversion.h>

Public Member Functions

- CX CoordinateConverter (ofPoint origin, bool invertX, bool invertY, bool invertZ=false)
- ofPoint operator() (ofPoint p)
- ofPoint operator() (float x, float y, float z=0)
- void setAxisInversion (bool invertX, bool invertY, bool invertZ=false)
- void setOrigin (ofPoint newOrigin)
- void setMultiplier (float multiplier)
- void setUnitConverter (CX BaseUnitConverter *converter)

13.7.1 Detailed Description

This helper class is used for converting from a somewhat user-defined coordinate system into the standard computer monitor coordinate system. When user coordinates are input into this class, they will be converted into the standard monitor coordinate system. This lets you use this class to allow you to use coordinates in your own system and convert those coordinates into the standard coordinates that are used by the drawing functions of openFrameworks.

See setUnitConverter() for a way to do change the units of the coordinate system to, for example, inches or degrees of visual angle.

Example use:

Another example can be found in the advancedChangeDetectionTask example experiment.

13.7.2 Constructor & Destructor Documentation

13.7.2.1 CX::Util::CX_CoordinateConverter::CX_CoordinateConverter (ofPoint *origin,* bool *invertX,* bool *invertY,* bool *invertY* bool *invertZ* = false)

Constructs a coordinate converter with the given settings.

Parameters

origin	The location within the standard coordinate system at which the origin (the point at which the x,	
	y, and z values are 0) of the user-defined coordinate system is located. If, for example, you war	
	the center of the display to be the origin within your user-defined coordinate system, you could	
	use CX_Display::getCenterOfDisplay() as the value for this argument.	
invertX	ertX Invert the x-axis from the default, which is that x increases to the right.	
invertY	Invert the y-axis from the default, which is that y increases downward.	
invertZ	Invert the z-axis from the default, which is that z increases toward the user (i.e. pointing out of	
	the front of the screen).	

13.7.3 Member Function Documentation

13.7.3.1 ofPoint CX::Util::CX_CoordinateConverter::operator() (ofPoint p)

The primary method of conversion between coordinate systems. You supply a point in user coordinates and get in return a point in standard coordinates.

Example use:

```
CX_CoordinateConverter cc(ofPoint(200,200), false, true); ofPoint p(-50, 100); //P is in user-defined coordinates, 50 units left and 100 units above the origin. ofPoint res = cc(p); //Use operator() to convert from the user system to the standard system. //res should contain (150, 100) due to the inverted y axis.
```

Parameters

р	The point in user coordinates that should be converted to standard coordinates.

Returns

The point in standard coordinates.

```
13.7.3.2 ofPoint CX::Util::CX_CoordinateConverter::operator() ( float x, float y, float z = 0 )
```

Equivalent to a call to operator()(ofPoint(x, y, z)).

13.7.3.3 void CX::Util::CX_CoordinateConverter::setAxisInversion (bool invertX, bool invertY, bool invertZ = false)

Sets whether each axis within the user-defined system is inverted from the standard coordinate system.

Parameters

invertX	Invert the x-axis from the default, which is that x increases to the right.	
invertY	Invert the y-axis from the default, which is that y increases downward.	
invertZ	Invert the z-axis from the default, which is that z increases toward the viewer (i.e. pointing out o	
	the front of the screen).	

13.7.3.4 void CX::Util::CX_CoordinateConverter::setMultiplier (float multiplier)

This function sets the amount by which user coordinates are multiplied before they are converted to standard coordinates. This allows you to easily scale stimuli. The multiplier is 1 by default.

Parameters

multiplier The amount to	to multiply user coordinates by.
--------------------------	----------------------------------

13.7.3.5 void CX::Util::CX_CoordinateConverter::setOrigin (ofPoint newOrigin)

Sets the location within the standard coordinate system at which the origin of the user-defined coordinate system is located.

Parameters

newOrigin	The location within the standard coordinate system at which the origin (the point at which the x,	
	y, and z values are 0) of the user-defined coordinate system is located. If, for example, you want	
	the center of the display to be the origin within your user-defined coordinate system, you could	
	use CX_Display::getCenterOfDisplay() as the value for this argument.	

```
13.7.3.6 void CX::Util::CX_CoordinateConverter::setUnitConverter ( CX_BaseUnitConverter * converter )
```

Sets the unit converter that will be used when converting the coordinate system. In this way you can convert both the coordinate system in use and the units used by the coordinate system in one step. See CX_DegreeToPixelConverter and CX_LengthToPixelConverter for examples of the converters that can be used.

Example use:

Parameters

converter

A pointer to an instance of a class that is a CX_BaseUnitConverter or which has inherited from that class. See CX_UnitConversion.h/cpp for the implementation of CX_LengthToPixelConverter to see an example of how to create you own converter.

Note

The origin of the coordinate converter must be in the units that result from the unit conversion. E.g. if you are converting the units from degrees to pixels, the origin must be in pixels. See setOrigin().

The unit converter passed to this function must continue to exist throughout the lifetime of the coordinate converter. It is not copied.

The documentation for this class was generated from the following files:

- · CX UnitConversion.h
- CX_UnitConversion.cpp

13.8 CX::CX DataFrame Class Reference

```
#include <CX_DataFrame.h>
```

Public Types

typedef std::vector
 CX_DataFrameCell >
 ::size_type rowIndex_t

Public Member Functions

- CX_DataFrame & operator= (CX_DataFrame &df)
- CX_DataFrameCell operator() (std::string column, rowIndex_t row)
- CX_DataFrameCell operator() (rowIndex_t row, std::string column)
- CX DataFrameCell at (rowIndex t row, std::string column)

- CX_DataFrameCell at (std::string column, rowIndex_t row)
- CX_DataFrameColumn operator[] (std::string column)
- CX_DataFrameRow operator[] (rowIndex_t row)
- void appendRow (CX_DataFrameRow row)
- void setRowCount (rowIndex t rowCount)
- void addColumn (std::string columnName)
- std::string print (std::string delimiter="\t", bool printRowNumbers=true)
- std::string print (const std::set< std::string > &columns, std::string delimiter="\t", bool printRowNumbers=true)
- std::string print (const std::vector< rowIndex_t > &rows, std::string delimiter="\t", bool printRowNumbers=true)
- std::string print (const std::set< std::string > &columns, const std::vector< rowIndex_t > &rows, std::string delimiter="\t", bool printRowNumbers=true)
- bool printToFile (std::string filename, std::string delimiter="\t", bool printRowNumbers=true)
- bool printToFile (std::string filename, const std::set< std::string > &columns, std::string delimiter="\t", bool print-RowNumbers=true)
- bool printToFile (std::string filename, const std::vector < rowIndex_t > &rows, std::string delimiter="\t", bool print-RowNumbers=true)
- bool printToFile (std::string filename, const std::set< std::string > &columns, const std::vector< rowIndex_t > &rows, std::string delimiter="\t", bool printRowNumbers=true)
- bool readFromFile (std::string filename, std::string cellDelimiter="\t", std::string vectorEncloser="\"")
- void clear (void)
- bool deleteColumn (std::string columnName)
- bool deleteRow (rowIndex_t row)
- std::vector< std::string > columnNames (void)
- rowIndex t getRowCount (void)

Returns the number of rows in the data frame.

- bool reorderRows (const vector < CX DataFrame::rowIndex t > &newOrder)
- CX_DataFrame copyRows (vector < CX_DataFrame::rowIndex_t > rowOrder)
- CX_DataFrame copyColumns (vector< std::string > columns)
- void shuffleRows (void)
- void shuffleRows (CX RandomNumberGenerator &rng)
- template < typename T > std::vector < T > copyColumn (std::string column)

Protected Member Functions

- void resizeToFit (std::string column, rowIndex t row)
- void resizeToFit (rowIndex t row)
- void _resizeToFit (std::string column)
- void _equalizeRowLengths (void)

Protected Attributes

- std::map< std::string, vectorCX DataFrameCell >> _ data
- rowIndex_t _rowCount

Friends

- · class CX DataFrameRow
- class CX_DataFrameColumn

13.8.1 Detailed Description

This class provides and easy way to store data from an experiment and output that data to a file at the end of the experiment. A CX_DataFrame is a square two-dimensional array of cells, but each cell is capable of holding a vector of data. Each cell is indexed with a column name (a string) and a row number. Cells can store many different kinds of data and the data can be inserted or extracted easily. The standard method of storing data is to use operator(), which dynamically resizes the data frame. When an experimental session is complete, the data can be written to a file using printToFile().

See the example dataFrame.cpp for thorough examples of how to use a CX_DataFrame.

Several of the member functions of this class could be blocking if the amount of data in the data frame is large enough.

13.8.2 Member Function Documentation

13.8.2.1 void CX_DataFrame::addColumn (std::string columnName)

Adds a column to the data frame.

Parameters

columnName	The name of the column to add. If a column with that name already exists in the data frame, a
	warning will be logged.

13.8.2.2 void CX_DataFrame::appendRow (CX_DataFrameRow row)

Appends the row to the end of the data frame.

Parameters

row The row to add.	
---------------------	--

Note

If the row has columns that do not exist in the data frame, those columns will be added to the data frame.

13.8.2.3 CX_DataFrameCell CX_DataFrame::at (rowIndex_t row, std::string column)

Access the cell at the given row and column with bounds checking. Throws a std::out_of_range exception and logs an error if either the row or column is out of bounds.

Parameters

row	The row number.
column	The column name.

Returns

A CX DataFrameCell that can be read from or written to.

13.8.2.4 void CX_DataFrame::clear (void)

Deletes the contents of the data frame. Resizes the data frame to have no rows and no columns.

13.8.2.5 std::vector < std::string > CX_DataFrame::columnNames (void)

Returns a vector containing the names of the columns in the data frame.

Returns

Vector of strings with the column names.

13.8.2.6 template < typename T > std::vector < T > CX::CX_DataFrame::copyColumn (std::string column)

Makes a copy of the data contained in the named column, converting it to the specified type (such a conversion must be possible).

Parameters

column	The name of the column to copy data from.

Returns

A vector containing the copied data.

13.8.2.7 CX DataFrame CX_DataFrame::copyColumns (vector < std::string > columns)

Copies the specified columns into a new data frame.

Parameters

columns	A vector of column names to copy out. If a requested column is not found, a warning will be	
	logged, but the function will otherwise complete successfully.	

Returns

A CX_DataFrame containing the specified columns.

Note

This function may be Blocking Code if the amount of copied data is large.

13.8.2.8 CX_DataFrame CX_DataFrame::copyRows (vector < CX_DataFrame::rowIndex_t > rowOrder)

Creates CX_DataFrame containing a copy of the rows specified in rowOrder. The new data frame is not linked to the existing data frame.

Parameters

rowOrder	A vector of CX_DataFrame::rowIndex_t containing the rows from this data frame to be copied out.	
	The indices in rowOrder may be in any order: They don't need to be ascending. Additionally, the	
	same row to be copied may be specified multiple times.	

Returns

A CX DataFrame containing the rows specified in rowOrder.

Note

This function may be Blocking Code if the amount of copied data is large.

13.8.2.9 bool CX_DataFrame::deleteColumn (std::string columnName)

Deletes the given column of the data frame.

Parameters

columnName	The name of the column to delete.	If the column is not in the data frame, a warning will be
	logged.	

Returns

True if the column was found and deleted, false if it was not found.

13.8.2.10 bool CX_DataFrame::deleteRow (rowIndex_t row)

Deletes the given row of the data frame.

Parameters

row	The row to delete (0 indexed). If row is greater than or equal to the number of rows in the data
	frame, a warning will be logged.

Returns

True if the row was in bounds and was deleted, false if the row was out of bounds.

13.8.2.11 CX_DataFrameCell CX_DataFrame::operator() (std::string column, rowIndex_t row)

Access the cell at the given row and column. If the row or column is out of bounds, the data frame will be dynamically resized in order to fit the row or column.

Parameters

row	The row number.
column	The column name.

Returns

A CX_DataFrameCell that can be read from or written to.

13.8.2.12 CX DataFrame & CX_DataFrame::operator= (CX DataFrame & df)

Copy the contents of another CX_DataFrame to this data frame. Because this is a copy operation, this may be Blocking Code if the copied data frame is large enough.

Parameters

df	The data frame to copy.
----	-------------------------

Returns

A reference to this data frame.

Note

The contents of this data frame are deleted during the copy.

13.8.2.13 std::string CX_DataFrame::print (std::string delimiter = "\t", bool printRowNumbers = true)

Reduced argument version of print(). Prints all rows and columns.

13.8.2.14 std::string CX_DataFrame::print (const std::set< std::string > & columns, std::string delimiter = "\t", bool printRowNumbers = true)

Reduced argument version of print(). Prints all rows and the selected columns.

13.8.2.15 std::string CX_DataFrame::print (const std::vector< rowIndex_t > & rows, std::string delimiter = "\t", bool printRowNumbers = true)

Reduced argument version of print(). Prints all columns and the selected rows.

13.8.2.16 std::string CX_DataFrame::print (const std::set< std::string > & columns, const std::vector< rowlndex_t > & rows, std::string delimiter = "\t", bool printRowNumbers = true)

Prints the selected rows and columns of the data frame to a string. Each cell of the data frame will be separated with the selected delimiter.

Each row of the data frame will be ended with a new line (whatever std::endl evaluates to, typically "\r\n").

Parameters

columns	Columns to print. Column names not found in the data frame will be ignored with a warning.
rows	Rows to print. Row indices not found in the data frame will be ignored with a warning.
delimiter	Delimiter to be used between cells of the data frame. Using comma or semicolon for the delimiter
	is not recommended because semicolons are used as element delimiters in the string-encoded
	vectors stored in the data frame and commas are used for element delimiters within each element
	of the string-encoded vectors.
printRow-	If true, a column will be printed with the header "rowNumber" with the contents of the column
Numbers	being the selected row indices. If false, no row numbers will be printed.

Returns

A string containing the printed version of the data frame.

Note

This function may be Blocking Code if the data frame is large enough.

13.8.2.17 bool CX_DataFrame::printToFile (std::string filename, std::string delimiter = "\t", bool printRowNumbers = true)

Reduced argument version of printToFile(). Prints all rows and columns.

13.8.2.18 bool CX_DataFrame::printToFile (std::string filename, const std::set< std::string > & columns, std::string delimiter = "\t", bool printRowNumbers = true)

Reduced argument version of printToFile(). Prints all rows and the selected columns.

13.8.2.19 bool CX_DataFrame::printToFile (std::string *filename*, const std::vector< rowIndex_t > & rows, std::string *delimiter* = "\t", bool *printRowNumbers* = true)

Reduced argument version of printToFile(). Prints all columns and the selected rows.

13.8.2.20 bool CX_DataFrame::printToFile (std::string *filename*, const std::set< std::string > & *columns*, const std::vector< rowlndex_t > & *rows*, std::string *delimiter* = "\t", bool *printRowNumbers* = true)

This function is equivalent in behavior to print() except that instead of returning a string containing the printed contents of the data frame, the string is printed to a file. If the file exists, it will be overwritten.

Parameters

filename	Name of the file to print to. If it is an absolute path, the file will be put there. If it is a local path,
	the file will be placed relative to the data directory of the project.

Returns

True for success, false if there was some problem writing to the file (insufficient permissions, etc.)

13.8.2.21 bool CX_DataFrame::readFromFile (std::string *filename*, std::string *cellDelimiter* = "\t", std::string *vectorEncloser* = "\"")

Reads data from the given file into the data frame. This function assumes that there will be a row of column names as the first row of the file. It does not treat consecutive delimiters as a single delimiter.

Parameters

filename	The name of the file to read data from. If it is a relative path, the file will be read relative to the
	data directory.
cellDelimiter	A string containing the delimiter between cells of the data frame.
vectorEncloser	A string containing the characters that surround cell that contain a vector of data. By default, vectors are enclosed in double quotes. This indicates to most software that it should treat the contents of the quotes "as-is", i.e. if it finds a delimiter within the quotes, it should not split there, but wait until out of the quotes.

Returns

False if an error occurred, true otherwise.

Note

The contents of the data frame will be deleted before attempting to read in the file.

If the data is read in from a file written with a row numbers column, that column will be read into the data frame. You can remove it using deleteColumn("rowNumber").

This function may be Blocking Code if the read in data frame is large enough.

13.8.2.22 bool CX_DataFrame::reorderRows (const vector < CX_DataFrame::rowIndex_t > & newOrder)

Re-orders the rows in the data frame.

Parameters

newOrder	Vector of row indices. newOrder.size() must equal this->getRowCount(). newOrder must not
	contain any out-of-range indices (i.e. they must be < getRowCount()). Both of these error
	conditions are checked for in the function call and errors are logged.

Returns

true if all of the conditions of newOrder are met, false otherwise.

13.8.2.23 void CX_DataFrame::setRowCount (rowIndex_t rowCount)

Sets the number of rows in the data frame.

Parameters

rowCount	The new number of rows in the data frame.
----------	---

Note

If the row count is less than the number of rows already in the data frame, it will delete those rows with a warning.

```
13.8.2.24 void CX_DataFrame::shuffleRows ( void )
```

Randomly re-orders the rows of the data frame using CX::Instances::RNG as the random number generator for the shuffling.

Note

This function may be Blocking Code if the data frame is large.

13.8.2.25 void CX_DataFrame::shuffleRows (CX RandomNumberGenerator & rng)

Randomly re-orders the rows of the data frame.

Parameters

rng Reference to a CX_RandomNumberGenerator to be used for the shuffling.

Note

This function may be Blocking Code if the data frame is large.

The documentation for this class was generated from the following files:

- · CX_DataFrame.h
- CX DataFrame.cpp

13.9 CX::CX DataFrameCell Class Reference

```
#include <CX_DataFrameCell.h>
```

Public Member Functions

- CX_DataFrameCell (const char *c)
- template<typename T >
 - CX DataFrameCell (const T &value)

Construct the cell, assigning the value to it.

• template<typename T >

CX_DataFrameCell (const std::vector< T > &values)

Construct the cell, assigning the values to it.

- CX_DataFrameCell & operator= (const char *c)
- template<typename T >

CX_DataFrameCell & operator= (const T &value)

Assigns a value to the cell.

```
    template<typename T >

  CX DataFrameCell & operator= (const std::vector < T > &values)
      Assigns a vector of values to the cell.
• template<typename T >
  operator T (void) const
      Attempts to convert the contents of the cell to T using to().
• template<typename T >
  operator std::vector< T > (void) const
      Attempts to convert the contents of the cell to vector< T > using to Vector<math>< T > ().
template<typename T >
  void store (const T &value)

    template<typename T >

  T to (void) const

    std::string toString (void) const

      Returns a copy of the stored data in the internal string representation. Type checking is not done because this is a lossless
      operation.

    bool toBool (void) const

      Returns a copy of the stored data converted to bool. Equivalent to to < bool> ().
• int tolnt (void) const
      Returns a copy of the stored data converted to int. Equivalent to to<int>().
· double toDouble (void) const
      Returns a copy of the stored data converted to double. Equivalent to to<double>().
• template<typename T >
  std::vector < T > toVector (void) const
```

void storeVector (std::vector< T > values) void copyCellTo (CX DataFrameCell *targetCell)

- std::string getStoredType (void)
- template<> std::string to (void) const

• template<typename T >

13.9.1 Detailed Description

This class manages the contents of a single cell in a CX_DataFrame. It handles all of the type conversion nonsense that goes on when data is inserted into or extracted from a data frame. It tracks the type of the data that is inserted or extracted and logs warnings if the inserted type does not match the extracted type, with a few exceptions (see notes).

Note

There are a few exceptions to the type tracking. If the inserted type is const char*, it is treated as a string. Additionally, you can extract anything as string without a warning. This is because the data is stored as a string internally so extracting the data as a string is a lossless operation.

13.9.2 Constructor & Destructor Documentation

13.9.2.1 CX_DataFrameCell::CX_DataFrameCell (const char * c)

Constructs the cell with a string literal, treating it as a std::string.

13.9.3 Member Function Documentation

13.9.3.1 void CX_DataFrameCell::copyCellTo (CX_DataFrameCell * targetCell)

Copies the contents of this cell to targetCell, including type information.

Parameters

targetCell	A pointer to the cell to copy data to.

13.9.3.2 std::string CX_DataFrameCell::getStoredType (void)

Gets a string representing the type of data stored within the cell. This string is implementation-defined (which is the C++ standards committee way of saying "It can be anything at all"). It is only guranteed to be the same for the same type, but not neccessarily be different for different types.

Returns

A string containing the name of the stored type as given by typeid(typename).name().

13.9.3.3 CX DataFrameCell & CX_DataFrameCell::operator= (const char * c)

Assigns a string literal to the cell, treating it as a std::string.

13.9.3.4 template < typename T > void CX::CX_DataFrameCell::store (const T & value)

Stores the given value with the given type. This function is a good way to explicitly state the type of the data you are storing into the cell if, for example, it is a literal.

Template Parameters

< <i>T</i> >	The type to store the value as. If T is not specified, this function is essentially equiv-
	alent to using operator=.

Parameters

value	The value to store.

13.9.3.5 template < typename T > void CX::CX_DataFrameCell::storeVector (std::vector < T > values)

Stores a vector of data in the cell. The data is stored as a string with each element delimited by a semicolon. If the data to be stored are strings containing semicolons, the data will not be extracted properly.

Parameters

values A vector of values to store.

13.9.3.6 template < typename T > T CX::CX_DataFrameCell::to (void) const

Attempts to convert the contents of the cell to type T. There are a variety of reasons why this conversion can fail and they all center on the user inserting data of one type and then attempting to extract data of a different type. Regardless of whether the conversion is possible, if you try to extract a type that is different from the type that is stored in the cell, a warning will be logged.

Template Parameters

< <i>T</i> >	The type to convert to.

Returns

The data in the cell converted to T.

13.9.3.7 std::string CX::CX_DataFrameCell::to (void) const

Equivalent to a call to toString(). This is specialized because it skips the type checks of to<T>.

Returns

A copy of the stored data encoded as a string.

13.9.3.8 template < typename T > std::vector < T > CX::CX_DataFrameCell::toVector (void) const

Returns a copy of the contents of the cell converted to a vector of the given type. If the type of data stored in the cell was not a vector of the given type or the type does match but it was a scalar that is stored, the logs a warning but attempts the conversion anyway.

Template Parameters

< <i>T</i> >	The type of the elements of the returned vector.

Returns

A vector containing the converted data.

The documentation for this class was generated from the following files:

- CX_DataFrameCell.h
- CX_DataFrameCell.cpp

13.10 CX::CX_DataFrameColumn Class Reference

Public Member Functions

- CX_DataFrameCell operator[] (CX_DataFrame::rowIndex_t row)
- CX_DataFrame::rowIndex_t size (void)

Friends

· class CX DataFrame

13.10.1 Detailed Description

The documentation for this class was generated from the following files:

- CX_DataFrame.h
- CX_DataFrame.cpp

13.11 CX::CX_DataFrameRow Class Reference

Public Member Functions

- CX DataFrameCell operator[] (std::string column)
- vector< std::string > names (void)
- void clear (void)

Friends

· class CX DataFrame

13.11.1 Detailed Description

The documentation for this class was generated from the following files:

- · CX DataFrame.h
- CX_DataFrame.cpp

13.12 CX::Util::CX_DegreeToPixelConverter Class Reference

```
#include <CX_UnitConversion.h>
```

Inherits CX::Util::CX BaseUnitConverter.

Public Member Functions

- CX_DegreeToPixelConverter (float pixelsPerUnit, float viewingDistance, bool roundResult=false)
- float operator() (float degrees)

13.12.1 Detailed Description

This simple utility class is used for converting degrees of visual angle to pixels on a monitor. This class uses CX::Util:::degreesToPixels() internally. See also CX::Util::CX_CoordinateConverter for a way to also convert from one coordinate system to another.

Example use:

13.12.2 Constructor & Destructor Documentation

13.12.2.1 CX::Util::CX_DegreeToPixelConverter::CX_DegreeToPixelConverter (float pixelsPerUnit, float viewingDistance, bool roundResult = false)

Constructs an instance of a CX_DegreeToPixelConverter using the given settings.

Parameters

pixelsPerUnit	The number of pixels within one length unit (e.g. inches, centimeters). This can be measured by
	drawing a \sim 100-1000 pixel square on the screen and measuring the length of a side and dividing
	the number of pixels by the total length measured.

viewingDistance	The distance from the monitor that the participant will be viewing the screen from.
roundResult	If true, the result of conversions will be rounded to the nearest integer (i.e. pixel). For drawing
	certain kinds of stimuli (especially text) it can be helpful to draw on pixel boundaries.

13.12.3 Member Function Documentation

13.12.3.1 float CX::Util::CX_DegreeToPixelConverter::operator() (float degrees)

Converts the degrees to pixels based on the settings given during construction.

Parameters

degrees	The number of degrees of visual angle to convert to pixels.
---------	---

Returns

The number of pixels corresponding to the number of degrees of visual angle.

The documentation for this class was generated from the following files:

- · CX UnitConversion.h
- CX_UnitConversion.cpp

13.13 CX::CX_Display Class Reference

#include <CX_Display.h>

Public Member Functions

- void setup (void)
- · void setFullScreen (bool fullScreen)
- void drawFboToBackBuffer (ofFbo &fbo)
- void drawFboToBackBuffer (ofFbo &fbo, ofRectangle placement)
- void beginDrawingToBackBuffer (void)
- void endDrawingToBackBuffer (void)
- void BLOCKING swapFrontAndBackBuffers (void)
- void swapFrontAndBackBuffers (void)
- void BLOCKING_setAutoSwapping (bool autoSwap)
- bool isAutomaticallySwapping (void)
- bool hasSwappedSinceLastCheck (void)
- CX_Micros getLastSwapTime (void)
- CX_Micros getFramePeriod (void)
- void setWindowResolution (int width, int height)
- void setWindowTitle (std::string title)
- ofRectangle getResolution (void)
- ofPoint getCenterOfDisplay (void)
- uint64_t getFrameNumber (void)
- void BLOCKING_estimateFramePeriod (CX_Micros estimationInterval)
- CX_Micros estimateNextSwapTime (void)
- void BLOCKING_waitForOpenGL (void)

13.13.1 Detailed Description

This class represents an abstract visual display surface, which is my way of saying that it doesn't necessarily represent a monitor. The display surface can either be a window or, if full screen, the whole monitor. It is also a bit abstract in that it does not draw anything, but only creates an context in which things can be drawn.

13.13.2 Member Function Documentation

13.13.2.1 void CX_Display::beginDrawingToBackBuffer (void)

Prepares a rendering context for using drawing functions. Must be paired with a call to endDrawingToBackBuffer().

13.13.2.2 void CX_Display::BLOCKING_estimateFramePeriod (CX_Micros estimationInterval)

This function estimates the typical period of the display refresh. This function blocks for estimationInterval while the swapping thread swaps in the background. This function is called with an argument of 300 ms during construction of this class, so there will always be some information about the frame period. If more precision of the estimate is desired, this function can be called again with a longer wait duration.

Parameters

a atimatian Interval	The length of time to around estimating the frame paried
estimationinterval	The length of time to spend estimating the frame period.

See Also

Blocking Code

13.13.2.3 void CX_Display::BLOCKING_setAutoSwapping (bool autoSwap)

Set whether the front and buffers of the display will swap automatically every frame or not. You can check to see if a swap has occured by calling hasSwappedSinceLastCheck(). You can check to see if the display is automatically swapping by calling isAutomaticallySwapping().

Parameters

autoSwap	If true, the front and back buffer will swap automatically every frame.
----------	---

See Also

Blocking Code

13.13.2.4 void CX_Display::BLOCKING_swapFrontAndBackBuffers (void)

This function queues up a swap of the front and back buffers then blocks until the swap occurs. It does nothing if isAutomaticallySwapping() == true.

See Also

Blocking Code

13.13.2.5 void CX_Display::BLOCKING_waitForOpenGL (void)

Wait until all OpenGL instructions that were given before this was called to complete. Any commands put into the pipeline from other threads after this is called are not waited for.

See Also

Blocking Code

13.13.2.6 void CX_Display::drawFboToBackBuffer (ofFbo & fbo)

Draw the given of Fbo to the back buffer. It will be drawn starting from 0, 0 and will be drawn at the full dimensions of the of Fbo (whatever size was chosen at allocation of the fbo).

13.13.2.7 void CX_Display::drawFboToBackBuffer (ofFbo & fbo, ofRectangle rect)

Draw the given of Fbo to the back buffer at the coordinates given by rect.

Parameters

fbo	The fbo to draw.
rect	The rectangle in which to place to fbo. The x and y components specify location. The width and
	height components specify the output width and height of the fbo. If these are not equal to the
	width and height of the fbo, the fbo will be scaled up or down to fit the width and height.

13.13.2.8 void CX_Display::endDrawingToBackBuffer (void)

Finish rendering to the back buffer. Must be paired with a call to beginDrawingToBackBuffer().

13.13.2.9 CX_Micros CX_Display::estimateNextSwapTime (void)

Get an estimate of the next time the front and back buffers will be swapped. This function depends on the precision of the frame period as estimated using BLOCKING estimateFramePeriod().

Returns

A time value that can be compared to CX::Instances::Clock.getTime().

13.13.2.10 ofPoint CX_Display::getCenterOfDisplay (void)

Returns an ofPoint representing the center of the display. Works in either windowed or full screen mode.

13.13.2.11 uint64_t CX_Display::getFrameNumber (void)

This function returns the number of the last frame presented, as determined by number of front and back buffer swaps. It tracks buffer swaps that result from 1) the front and back buffer swapping automatically (as a result of BLOCKING_setAutoSwapping() with true as the argument) and 2) manual swaps resulting from a call to BLOCKING_swapFrontAnd-BackBuffers() or swapFrontAndBackBuffers().

Returns

The number of the last frame. This value can only be compared with other values returned by this function.

13.13.2.12 CX_Micros CX_Display::getFramePeriod (void)

Gets the estimate of the frame period calculated with BLOCKING_estimateFramePeriod().

13.13.2.13 CX_Micros CX_Display::getLastSwapTime (void)

Get the last time at which the front and back buffers were swapped.

Returns

A time value that can be compared with CX::Instances::Clock.getTime().

13.13.2.14 ofRectangle CX_Display::getResolution (void)

Returns the resolution of the current window, not the resolution of the monitor (unless you are in full screen mode).

Returns

An ofRectangle containing the resolution. The width in pixels is stored in both the width and x members and the height in pixles is stored in both the height and y members, so you can use whichever makes the most sense to you.

13.13.2.15 bool CX_Display::hasSwappedSinceLastCheck (void)

Check to see if the display has swapped the front and back buffers since the last call to this function. This is generally used in conjuction with automatic swapping of the buffers (BLOCKING_setAutoSwapping()) or with an individual threaded swap of the buffers (swapFrontAndBackBuffers()). This technically works with BLOCKING_swapFrontAndBackBuffers(), but given that that function only returns once the buffers have swapped, checking that the buffers have swapped is redundant.

Returns

True if a swap has been made since the last call to this function, false otherwise.

13.13.2.16 bool CX_Display::isAutomaticallySwapping (void)

Determine whether the display is configured to automatically swap the front and back buffers every frame. See BLOC-KING setAutoSwapping for more information.

13.13.2.17 void CX_Display::setFullScreen (bool fullScreen)

Set whether the display is full screen or not. If the display is set to full screen, the resolution may not be the same as the resolution of display in windowed mode, and vice versa.

13.13.2.18 void CX_Display::setup (void)

Set up the display. Must be called for the display to function correctly.

13.13.2.19 void CX_Display::setWindowResolution (int width, int height)

Sets the resolution of the window. Has no effect if called while in full screen mode.

Parameters

width	The desired width of the window, in pixels.
height	The desired height of the window, in pixels.

13.13.2.20 void CX_Display::setWindowTitle (std::string title)

Sets the title of the experiment window.

Parameters

title	The new window title.

13.13.2.21 void CX_Display::swapFrontAndBackBuffers (void)

This function cues a swap of the front and back buffers. It avoids blocking (like BLOCKING_swapFrontAndBackBuffers()) by spawning a thread in which the swap is waited for.

The documentation for this class was generated from the following files:

- · CX Display.h
- CX_Display.cpp

13.14 CX::CX_InputManager Class Reference

```
#include <CX_InputManager.h>
```

Public Member Functions

- bool setup (bool useKeyboard, bool useMouse, int joystickIndex=-1)
- bool pollEvents (void)

Public Attributes

• CX_Keyboard Keyboard

An instance of CX::CX_Keyboard. Enabled or disabled with CX::CX_InputManager::setup().

CX Mouse Mouse

An instance of CX::CX_Mouse. Enabled or disabled with CX::CX_InputManager::setup().

CX_Joystick Joystick

An instance of CX::CX_Joystick. Enabled or disabled with CX::CX_InputManager::setup().

13.14.1 Detailed Description

This class is responsible for managing three basic input devices: a keyboard, mouse, and joystick. You access each of these devices with the corresponding member class: Keyboard, Mouse, and Joystick. See CX::CX_Keyboard, CX::CX_Mouse, and CX::CX_Joystick for more information about each specific device.

By default, all three input devices are disabled. Call setup() to enable specific devices.

13.14.2 Member Function Documentation

13.14.2.1 bool CX_InputManager::pollEvents (void)

It is not typically neccessary for the user to call this function directly, although there is no harm in doing so. This function polls for new events on all of the configured input devices (see setup()). After a call to this function, new events for the input devices can be found by checking the available Events() function for each device.

Returns

True if there are any events available for enabled devices, false otherwise. The events do not neccessarily need to be new events. If there are events that were already stored in Mouse, Keyboard, or Joystick but had not been processed by user code, this function will return true.

13.14.2.2 bool CX_InputManager::setup (bool useKeyboard, bool useMouse, int joystickIndex = -1)

Setup the input manager to use the requested devices. You may call this function multiple times if you want to change the configuration over the course of the experiment. Every time this function is called, all input device events are cleared.

Parameters

useKeyboard	Enable or disable the keyboard.
useMouse	Enable or disable the mouse.
joystickIndex	Optional. If \geq = 0, an attempt will be made to set up the joystick at that index. If $<$ 0, no attempt
	will be made to set up the joystick.

Returns

False if the requested joystick could not be set up correctly, true otherwise.

The documentation for this class was generated from the following files:

- · CX InputManager.h
- CX InputManager.cpp

13.15 CX::CX_Joystick Class Reference

#include <CX_Joystick.h>

Classes

• struct Event

Public Member Functions

- bool setup (int joystickIndex)
- std::string getJoystickName (void)
- bool pollEvents (void)
- int availableEvents (void)
- CX Joystick::Event getNextEvent (void)
- void clearEvents (void)
- std::vector< float > getAxisPositions (void)
- std::vector< unsigned char > getButtonStates (void)

13.15.1 Detailed Description

This class manages a joystick that is attached to the system (if any). If more than one joystick is needed for the experiment, you can create more instances of CX Joystick other than the one in CX::Instances::Input.

13.15.2 Member Function Documentation

```
13.15.2.1 int CX_Joystick::availableEvents ( void )
```

Get the number of new events available for this input device.

```
13.15.2.2 void CX_Joystick::clearEvents ( void )
```

Clear (delete) all events from this input device.

```
13.15.2.3 vector < float > CX_Joystick::getAxisPositions (void)
```

This function is to be used for direct access to the axis positions of the joystick. It does not generate events (i.e. CX_Joystick::Event), nor does it do any timestamping. If timestamps and uncertainies are desired, you MUST use pollEvents() and the associated event functions (e.g. getNextEvent()).

```
13.15.2.4 vector < unsigned char > CX_Joystick::getButtonStates ( void )
```

This function is to be used for direct access to the button states of the joystick. It does not generate events (i.e. CX_Joystick::Event), nor does it do any timestamping. If timestamps and uncertainies are desired, you MUST use pollEvents() and the associated event functions (e.g. getNextEvent()).

```
13.15.2.5 std::string CX_Joystick::getJoystickName (void)
```

Get the name of the joystick, presumably as set by the joystick driver. The name may not be very meaningful.

```
13.15.2.6 CX_Joystick::Event CX_Joystick::getNextEvent ( void )
```

Get the next event available for this input device. This is a destructive operation: the returned event is deleted from the input device.

```
13.15.2.7 bool CX_Joystick::pollEvents ( void )
```

Check to see if there are any new joystick events. If there are new events, they can be accessed with availableEvents() and getNextEvent().

Returns

True if there are new events.

```
13.15.2.8 bool CX_Joystick::setup ( int joystickIndex )
```

Set up the joystick by attempting to initialize the joystick at the given index. If the joystick is present on the system, it will be initialized and its name can be accessed by calling getJoystickName().

If the set up is successful (i.e. if the selected joystick is present on the system), this function will return true. If the joystick is not present, it will return false.

The documentation for this class was generated from the following files:

- · CX Joystick.h
- · CX_Joystick.cpp

13.16 CX::CX_Keyboard Class Reference

```
#include <CX_Keyboard.h>
```

Classes

struct Event

Public Member Functions

- int availableEvents (void)
- CX_Keyboard::Event getNextEvent (void)
- void clearEvents (void)
- bool isKeyPressed (int key)

Friends

· class CX_InputManager

13.16.1 Detailed Description

This class is responsible for managing the mouse.

13.16.2 Member Function Documentation

```
13.16.2.1 int CX_Keyboard::availableEvents ( void )
```

Get the number of new events available for this input device.

```
13.16.2.2 void CX_Keyboard::clearEvents ( void )
```

Clear (delete) all events from this input device.

```
13.16.2.3 CX_Keyboard::Event CX_Keyboard::getNextEvent ( void )
```

Get the next event available for this input device. This is a destructive operation: the returned event is deleted from the input device.

```
13.16.2.4 bool CX::CX_Keyboard::isKeyPressed (int key ) [inline]
```

This function checks to see if the given key is pressed.

Parameters

key	The key code for key you are interested in. See the documentation for the key member of
	CX_Keyboard::Event for more information about this value.

Returns

True if the given key is held.

The documentation for this class was generated from the following files:

- · CX Keyboard.h
- CX_Keyboard.cpp

13.17 CX::Util::CX_LengthToPixelConverter Class Reference

```
#include <CX_UnitConversion.h>
```

Inherits CX::Util::CX_BaseUnitConverter.

Public Member Functions

- CX_LengthToPixelConverter (float pixelsPerUnit, bool roundResult=false)
- float operator() (float length)

13.17.1 Detailed Description

This simple utility class is used for converting lengths (perhaps of objects drawn on the monitor) to pixels on a monitor. See also CX::Util::CX CoordinateConverter for a way to also convert from one coordinate system to another.

Example use:

13.17.2 Constructor & Destructor Documentation

13.17.2.1 CX::Util::CX LengthToPixelConverter::CX LengthToPixelConverter (float pixelsPerUnit, bool roundResult = false)

Constructs a CX_LengthToPixelConverter with the given configuration.

Parameters

pixelsPerUnit	The number of pixels per one length unit. This can be measured by drawing a \sim 100-1000 pixel
	square on the screen and measuring the length of a side and dividing the number of pixels by
	the total length measured.
roundResult	If true, the result of conversions will be rounded to the nearest integer (i.e. pixel). For drawing
	certain kinds of stimuli (especially text) it can be helpful to draw on pixel boundaries.

13.17.3 Member Function Documentation

13.17.3.1 float CX::Util::CX_LengthToPixelConverter::operator() (float length)

Converts the length to pixels based on the settings given during construction.

Parameters

length	The length to convert to pixels.

Returns

The number of pixels corresponding to the length.

The documentation for this class was generated from the following files:

- · CX UnitConversion.h
- CX_UnitConversion.cpp

13.18 CX::CX_Logger Class Reference

```
#include <CX_Logger.h>
```

Public Member Functions

- std::stringstream & log (CX_LogLevel level, std::string module="")
- std::stringstream & verbose (std::string module="")
- std::stringstream & notice (std::string module="")
- std::stringstream & warning (std::string module="")
- std::stringstream & error (std::string module="")
- std::stringstream & fatalError (std::string module="")
- void level (CX_LogLevel level, std::string module="")
- void levelForConsole (CX_LogLevel level)
- void levelForFile (CX LogLevel level, std::string filename="CX DEFERRED LOGGER DEFAULT")
- void levelForAllModules (CX_LogLevel level)
- void flush (void)
- void timestamps (bool logTimestamps, std::string format="%H:%M:%S.%i")
- void setMessageFlushCallback (std::function < void(CX MessageFlushData &) > f)
- void captureOFLogMessages (void)

13.18.1 Detailed Description

This class is used for logging messages throughout the CX backend code. It can also be used in user code to log messages. Rather than instantiating your own copy of CX_Logger, it is probably better to use the preinstantiated CX::Instances::Log.

There is an example showing a number of the features of CX Logger named example-logging.

13.18.2 Member Function Documentation

```
13.18.2.1 void CX_Logger::captureOFLogMessages ( void )
```

Set this instance of CX_Logger to be the target of any messages created by oF logging functions.

```
13.18.2.2 std::stringstream & CX_Logger::error ( std::string module = " " )
```

This function is equivalent to a call to log(CX_LogLevel::LOG_ERROR, module).

```
13.18.2.3 std::stringstream & CX_Logger::fatalError ( std::string module = " " )
```

This function is equivalent to a call to log(CX_LogLevel::LOG_FATAL_ERROR, module).

```
13.18.2.4 void CX_Logger::flush (void)
```

Log all of the messages stored since the last call to flush() to the selected logging targets. This is a BLOCKING operation.

```
13.18.2.5 void CX_Logger::level ( CX_LogLevel level, std::string module = " " )
```

Sets the log level for the given module. Messages from that module that are at a lower level than level will be ignored.

Parameters

level	See the CX::CX_LogLevel enum for valid values.
module	A string representing one of the modules from which log messages are generated.

13.18.2.6 void CX_Logger::levelForAllModules (CX_LogLevel level)

Set the log level for all modules. This works both retroactively and proactively: All currently known modules are given the log level and the default log level for new modules as set to the level.

```
13.18.2.7 void CX_Logger::levelForConsole ( CX_LogLevel level )
```

Set the log level for messages to be printed to the console.

```
13.18.2.8 void CX_Logger::levelForFile ( CX_LogLevel level, std::string filename = "CX_DEFERRED_LOGGER_-DEFAULT" )
```

Sets the log level for the file with given file name. If the file does not exist, it will be created. If the file does exist, it will be overwritten with a warning logged to cerr.

Parameters

	level	See the CX_LogLevel enum for valid values.
filen	name	Optional. If no file name is given, a file with name generated from a date/time from the start time
		of the experiment will be used.

13.18.2.9 std::stringstream & CX_Logger::log (CX_LogLevel level, std::string module = " ")

This is the basic logging function for this class. Example use:

Log.log(CX LogLevel::LOG WARNING, "myModule") << "My message number " << 20;

Possible output: "[warning] <myModule> My message number 20"

Parameters

level	Log level for this message. This has implications for message filtering. See level(). This should
	not be LOG_ALL or LOG_NONE, because that would be weird, wouldn't it?
module	Name of the module that this log message is related to. This has implications for message
	filtering. See level().

Returns

A reference to a std::stringstream that the log message data should be streamed into.

```
13.18.2.10 std::stringstream & CX_Logger::notice ( std::string module = " " )
```

This function is equivalent to a call to log(CX LogLevel::LOG NOTICE, module).

```
13.18.2.11 void CX_Logger::setMessageFlushCallback ( std::function < void(CX_MessageFlushData &) > f )
```

Sets the user function that will be called on each message flush event. For every message that has been logged, the user function will be called. No filtering is performed: All messages regardless of the module log level will be sent to the user function.

Parameters

f	A pointer to a user function that takes a reference to a CX_MessageFlushData struct and returns
	nothing.

13.18.2.12 void CX_Logger::timestamps (bool logTimestamps, std::string format = "%H:%M:%S.%i")

Set whether or not to log timestamps and the format for the timestamps.

Parameters

logTimestamps	Does what it says.
format	Timestamp format string. See http://pocoproject.org/docs/Poco.DateTime-
	Formatter.html#4684 for documentation of the format. Defaults to H:M:S.i (24-hour clock with milliseconds at the end).

13.18.2.13 std::stringstream & CX_Logger::verbose (std::string module = " ")

This function is equivalent to a call to log(CX LogLevel::LOG VERBOSE, module).

13.18.2.14 std::stringstream & CX_Logger::warning (std::string module = " ")

This function is equivalent to a call to log(CX_LogLevel::LOG_WARNING, module).

The documentation for this class was generated from the following files:

- · CX_Logger.h
- CX_Logger.cpp

13.19 CX::CX Mouse Class Reference

#include <CX_Mouse.h>

Classes

struct Event

Public Member Functions

- int availableEvents (void)
- CX_Mouse::Event getNextEvent (void)
- void clearEvents (void)
- void showCursor (bool show)
- void setCursorPosition (ofPoint pos)
- ofPoint getCursorPosition (void)

Friends

· class CX_InputManager

13.19.1 Detailed Description

This class is responsible for managing the mouse.

13.19.2 Member Function Documentation

```
13.19.2.1 int CX_Mouse::availableEvents ( void )
```

Get the number of new events available for this input device.

```
13.19.2.2 void CX_Mouse::clearEvents ( void )
```

Clear (delete) all events from this input device.

```
13.19.2.3 ofPoint CX_Mouse::getCursorPosition ( void )
```

Get the cursor position within the program window. If the mouse has left the window, this will return the last known position of the cursor within the window.

Returns

An ofPoint with the last cursor position.

```
13.19.2.4 CX_Mouse::Event CX_Mouse::getNextEvent ( void )
```

Get the next event available for this input device. This is a destructive operation: the returned event is deleted from the input device.

13.19.2.5 void CX_Mouse::setCursorPosition (ofPoint pos)

Sets the position of the cursor, relative to the program the window. The window must be focused.

Parameters

pos	The location within the window to set the cursor.
-----	---

13.19.2.6 void CX_Mouse::showCursor (bool show)

Show or hide the mouse cursor within the program window. If in windowed mode, the cursor will be visible outside of the window.

Parameters

show	If true, the cursor will be shown, if false it will not be shown.

The documentation for this class was generated from the following files:

- CX Mouse.h
- CX_Mouse.cpp

13.20 CX::CX RandomNumberGenerator Class Reference

#include <CX_RandomNumberGenerator.h>

Public Member Functions

- CX RandomNumberGenerator (void)
- void setSeed (unsigned long seed)
- unsigned long getSeed (void)
- CX_RandomInt_t getMinimumRandomInt (void)
- CX RandomInt t getMaximumRandomInt (void)
- CX RandomInt t randomInt (void)
- CX_RandomInt_t randomInt (CX_RandomInt_t rangeLower, CX_RandomInt_t rangeUpper)
- template<typename T >

T randomExclusive (const std::vector< T > &values, const T &exclude)

• template<typename T >

T randomExclusive (const std::vector< T > &values, const std::vector< T > &exclude)

- double uniformDeviate (double lowerBound closed, double upperBound open)
- std::vector< double > uniformDeviates (unsigned int count, double lowerBound_closed, double upperBound_open)
- template<typename T >
 std::vector< T > binomialDeviates (unsigned int count, T trials, double probSuccess)
- std::vector< double > normalDeviates (unsigned int count, double mean, double standardDeviation)
- template<typename T > void shuffle Vector (std::vector< T > *v)
- template<typename T >
 std::vector< T > shuffleVector (std::vector< T > v)
- template<typename T >

T sample (std::vector< T > values)

- template<typename T >
 std::vector< T > sample (unsigned int count, const std::vector< T > &source, bool withReplacement)
- std::vector< int > sample (unsigned int count, int lowerBound, int upperBound, bool withReplacement)

13.20.1 Detailed Description

This class is used for generating random values from a pseudo-random number generator. If uses a version of the Mersenne Twister algorithm, in particular std::mt19937_64 (see http://en.cppreference.-com/w/cpp/numeric/random/mersenne_twister_engine for the parameters used with this algorithm).

The monolithic structure of CX_RandomNumberGenerator provides a certain important feature that a collection of loose function does not have, which is the ability to trivially track the random seed being used for the random number generator. The function CX_RandomNumberGenerator::setSeed() sets the seed for all random number generation tasks performed by this class. Likewise, CX_RandomNumberGenerator::getSeed() allows you to easily find the seed that is being used for random number generation. Due to this structure, you can easily save the seed that was used for each participant, which allows you to repeat the exact randomizations used for that participant (unless random number generation varies as a function of the responses given by a participant).

An instance of this class is preinstantiated for you. See CX::Instances::RNG for information about the instance.

13.20.2 Constructor & Destructor Documentation

13.20.2.1 CX_RandomNumberGenerator::CX_RandomNumberGenerator (void)

Constructs an instance of a CX_RandomNumberGenerator. Seeds the CX_RandomNumberGenerator using a std::random device.

By the C++11 specification, std::random_device is supposed to be a non-deterministic (hardware) RNG. However, from http://en.cppreference.com/w/cpp/numeric/random/random_device: "Note that std::random_device may be implemented in terms of a pseudo-random number engine if a non-deterministic source (e.g. a hardware device) is not available to the implementation." According to a Stack Overflow comment, Microsoft's implementation of std::random_device is based on a ton of stuff, which should result in a fairly random result to be used as a seed for our Mersenne Twister. See the comment: http://stackoverflow.-com/questions/9549357/the-implementation-of-random-device-in-vs2010/9575747#9575747

Although this data should have high entropy, it is not a hardware RNG. The random_device is only used to seed the Mersenne Twister, so as long as the initial value is random enough, it should be fine.

13.20.3 Member Function Documentation

13.20.3.1 template<typename T > std::vector< T > CX::CX_RandomNumberGenerator::binomialDeviates (unsigned int *count,* T *trials,* double *probSuccess*)

Samples count deviates from a binomial distribution with the given number of trials and probability of success on each trial.

Parameters

	count	The number of deviates to generate.
	trials	The number of trials. Must be a non-negative integer.
ļ	probSuccess	The probability of a success on a given trial, where a success is the value 1.

Returns

A vector of the deviates.

13.20.3.2 CX_RandomInt_t CX_RandomNumberGenerator::getMaximumRandomInt (void)

Get the maximum possible value that can be returned by randomInt().

Returns

The maximum value.

13.20.3.3 CX_RandomInt_t CX_RandomNumberGenerator::getMinimumRandomInt (void)

Get the minimum value that can be returned by randomInt().

Returns

The minimum value.

13.20.3.4 unsigned long CX_RandomNumberGenerator::getSeed (void)

Get the seed used to seed the random number generator.

Returns

The seed. May have been set by the user with setSeed() or during construction of the CX_RandomNumber-Generator.

13.20.3.5 std::vector< double > CX_RandomNumberGenerator::normalDeviates (unsigned int *count*, double *mean*, double *standardDeviation*)

Samples count deviates from a normal distribution with the given mean and standard deviation.

Parameters

count	The number of deviates to generate.
mean	The mean of the distribution.
standard-	The standard deviation of the distribution.
Deviation	

Returns

A vector of the deviates.

13.20.3.6 template<typename T > T CX::CX_RandomNumberGenerator::randomExclusive (const std::vector< T > & values, const T & exclude)

Get a random value from a vector, without the possibility of getting the excluded value.

Parameters

values	The vectors of values to sample from.
exclude	The value to exclude from sampling.

Returns

The sampled value.

Note

If all of the values are excluded, an error will be logged and T() will be returned.

13.20.3.7 template < typename T > T CX::CX_RandomNumberGenerator::randomExclusive (const std::vector < T > & values, const std::vector < T > & exclude)

Get a random value from a vector without the possibility of getting any of the excluded values.

Parameters

values	The vector of values to sample from.
exclude	The vector of values to exclude from sampling.

Returns

The sampled value.

Note

If all of the values are excluded, an error will be logged and T() will be returned.

13.20.3.8 CX_RandomInt_t CX_RandomNumberGenerator::randomInt (void)

Get a random integer in the range getMinimumRandomInt(), getMaximumRandomInt(), inclusive.

Returns

The int.

13.20.3.9 CX_RandomInt_t CX_RandomNumberGenerator::randomInt (CX_RandomInt_t min, CX_RandomInt_t max)

This function returns an integer from the range [rangeLower, rangeUpper]. The minimum and maximum values for the int returned from this function are given by getMinimumRandomInt() and getMaximumRandomInt().

If rangeLower > rangeUpper, the lower and upper ranges are swapped. If rangeLower == rangeUpper, it returns range-Lower.

13.20.3.10 template < typename T > T CX::CX_RandomNumberGenerator::sample (std::vector < T > values)

Returns a single value sampled randomly from values.

Returns

The sampled value.

Note

If values.size() == 0, an error will be logged and T() will be returned.

13.20.3.11 template < typename T > std::vector < T > CX::CX_RandomNumberGenerator::sample (unsigned int count, const std::vector < T > & source, bool withReplacement)

Returns a vector of count values drawn randomly from source, with or without replacement. The returned values are in a random order.

Parameters

count	The number of samples to draw.
source	A vector to be sampled from.
withReplacement	Sample with or without replacement.

Returns

A vector of the sampled values.

Note

If (count > source.size() && withReplacement == false), an empty vector is returned.

13.20.3.12 std::vector< int > CX_RandomNumberGenerator::sample (unsigned int *count*, int *lowerBound*, int *upperBound*, bool withReplacement)

Returns a vector of count integers drawn randomly from the range [lowerBound, upperBound] with or without replacement.

Parameters

count	The number of samples to draw.
lowerBound	The lower bound of the range to sample from. It is possible to sample this value.
upperBound	The upper bound of the range to sample from. It is possible to sample this value.

withReplacement

Returns

A vector of the samples.

13.20.3.13 void CX_RandomNumberGenerator::setSeed (unsigned long seed)

Set the seed for the random number generator. You can retrieve the seed with getSeed().

Parameters

seed	The new seed.

13.20.3.14 template < typename T > void CX::CX_RandomNumberGenerator::shuffleVector (std::vector < T > * v)

Randomizes the order of the given vector.

Parameters

V	A pointer to the vector to be shuffled.

13.20.3.15 template < typename T > std::vector < T > CX::CX_RandomNumberGenerator::shuffleVector (std::vector < T > ν)

Makes a copy of the given vector, randomizes the order of its elements, and returns the shuffled copy.

Parameters

V The vector to be operated on.

Returns

A shuffled copy of v.

13.20.3.16 double CX_RandomNumberGenerator::uniformDeviate (double lowerBound_closed, double upperBound_open)

Samples a deviate from a uniform distribution with the range [lowerBound_closed, upperBound_open).

Parameters

lowerBound	The lower bound of the distribution. This bound is closed, meaning that you can observe deviates
closed	with this value.
upperBound	The upper bound of the distribution. This bound is open, meaning that you cannot observe
open	deviates with this value.

Returns

The deviate.

13.20.3.17 std::vector< double > CX_RandomNumberGenerator::uniformDeviates (unsigned int *count*, double *lowerBound_closed*, double *upperBound_open*)

Samples count deviates from a uniform distribution with the range [lowerBound_closed, upperBound_open).

Parameters

	count	The number of deviates to generate.
lov	verBound	The lower bound of the distribution. This bound is closed, meaning that you can observe deviates
	closed	with this value.
ирі	perBound	The upper bound of the distribution. This bound is open, meaning that you cannot observe
	open	deviates with this value.

Returns

A vector of the deviates.

The documentation for this class was generated from the following files:

- · CX RandomNumberGenerator.h
- CX_RandomNumberGenerator.cpp

13.21 CX::CX_SlidePresenter Class Reference

#include <CX SlidePresenter.h>

Classes

- struct Configuration
- struct FinalSlideFunctionArgs
- struct PresentationErrorInfo
- struct Slide
- struct SlideTimingInfo

Public Types

enum ErrorMode { ErrorMode::PROPAGATE DELAYS, ErrorMode::FIX TIMING FROM FIRST SLIDE }

Public Member Functions

- bool setup (CX Display *display)
- bool setup (const CX_SlidePresenter::Configuration &config)
- virtual void update (void)
- void appendSlide (CX_SlidePresenter::Slide slide)
- void appendSlideFunction (void(*drawingFunction)(void), CX_Micros slideDuration, std::string slideName="")
- void beginDrawingNextSlide (CX_Micros slideDuration, std::string slideName="")
- void endDrawingCurrentSlide (void)
- bool startSlidePresentation (void)
- void stopSlidePresentation (void)

Stops slide presentation.

• bool isPresentingSlides (void) const

Returns true if slide presentation is in progress, even if the first slide has not yet been presented.

- void clearSlides (void)
- · std::vector

< CX SlidePresenter::Slide > & getSlides (void)

- std::vector < CX_Micros > getActualPresentationDurations (void)
- std::vector< unsigned int > getActualFrameCounts (void)
- CX_SlidePresenter::PresentationErrorInfo checkForPresentationErrors (void) const

Protected Member Functions

- unsigned int _calculateFrameCount (CX_Micros duration)
- void singleCoreBlockingUpdate (void)
- void _singleCoreThreadedUpdate (void)
- void _multiCoreUpdate (void)
- void _renderCurrentSlide (void)
- void _waitSyncCheck (void)
- void _finishPreviousSlide (void)
- void handleFinalSlide (void)
- void _prepareNextSlide (void)

Protected Attributes

- CX SlidePresenter::Configuration _config
- CX_Micros _hoggingStartTime
- · bool _presentingSlides
- bool_synchronizing
- · unsigned int _currentSlide
- · std::vector
 - < CX SlidePresenter::Slide > _slides
- · bool lastFramebufferActive
- bool useFenceSync
- bool _awaitingFenceSync
- GLsync _fenceSyncObject

13.21.1 Detailed Description

This class is a very useful abstraction that presents slides (typically a full display) of visual stimuli for fixed durations. See the basicChangeDetectionTask.cpp, advancedChangeDetectionTask.cpp, and nBack.cpp examples for the usage of this class.

A brief example:

```
CX_SlidePresenter slidePresenter;
slidePresenter.setup(&Display);

slidePresenter.beginDrawingNextSlide(2000 * 1000, "circle");
ofBackground(50);
ofSetColor(ofColor::red);
ofCircle(Display.getCenterOfDisplay(), 40);

slidePresenter.beginDrawingNextSlide(1000 * 1000, "rectangle");
ofBackground(50);
ofSetColor(ofColor::green);
ofRect(Display.getCenterOfDisplay() - ofPoint(100, 100), 200, 200);

slidePresenter.beginDrawingNextSlide(1, "off");
ofBackground(50);
slidePresenter.endDrawingCurrentSlide();
slidePresenter.startSlidePresentation();
//Update the slide presenter while waiting for slide presentation to complete
```

```
while (slidePresenter.isPresentingSlides()) {
    slidePresenter.update(); //You must remember to call update() regularly while slides are being
    presented!
}
```

13.21.2 Member Enumeration Documentation

```
13.21.2.1 enum CX::CX_SlidePresenter::ErrorMode [strong]
```

The settings in this enum are related to what a CX_SlidePresenter does when it encounters a timing error. Timing errors are probably almost exclusively related to one slide being presented for too long.

The PROPAGATE_DELAYS setting causes the slide presenter to handle these errors by moving the start time of all future stimuli back by the number of extra frame that the erroneous slide used. This makes the durations of all future stimuli correct, so that there is only an error in the duration of one slide.

An alternative option is to try to keep the onsets of all slides as constant as possible relative to each other. This means that if one slide is presented for an extra frame, the next slide will be presented for one frame less than it should have been. If one slide is presented for several extra frames (this should almost never happen), the next slide may be skipped altogether. However, this mode (FIX_TIMING_FROM_FIRST_SLIDE) does not completely work currently so it should not be used.

Enumerator

PROPAGATE_DELAYS This mode handles timing errors by changing the onset times of future stimuli so. **FIX_TIMING_FROM_FIRST_SLIDE** This does not work currently.

13.21.3 Member Function Documentation

```
13.21.3.1 void CX_SlidePresenter::appendSlide ( CX_SlidePresenter::Slide slide )
```

Add a fully configured slide to the end of the list of slides. The user code must configure several components of the slide:

- If the framebuffer will be used, the framebuffer must be allocated and drawn to.
- If the drawing function will be used, a valid function pointer must be given. A check is made that either the drawing function is set or the framebuffer is allocated and an error is logged if neither is configured.
- · The intended duration must be set.
- The name may be set (optional).

Parameters

slide The slide to append.	slide	The slide to append.
----------------------------	-------	----------------------

13.21.3.2 void CX_SlidePresenter::appendSlideFunction (void(*)(void) drawingFunction, CX_Micros slideDuration, std::string slideName = " ")

Appends a slide to the slide presenter that will call the given drawing function when it comes time to render the slide to the back buffer. Essentially, the drawing function will be called one frame before the front and back buffers are swapped.

Parameters

drawingFunction	A pointer to a function that will draw the data to the slide. The contents of the back buffer are not clear before this function is called, so the function must clear the background to the desired color.
slideDuration	The amount of time to present the slide for. If this is less than or equal to 0, the slide will be
	ignored.
slideName	The name of the slide. This can be anything and is purely for the user to use to help identify the
	slide.

13.21.3.3 void CX SlidePresenter::beginDrawingNextSlide (CX Micros slideDuration, std::string slideName = " ")

Prepares the framebuffer of the next slide for drawing so that any drawing commands given between a call to begin-DrawingNextSlide() and endDrawingCurrentSlide() will cause stimuli to be drawn to the framebuffer of the slide.

Parameters

	slideDuration	The amount of time to present the slide for. If this is less than or equal to 0, the slide will be
		ignored.
Ì	slideName	The name of the slide. This can be anything and is purely for the user to use to help identify the
		slide.

13.21.3.4 CX SlidePresenter::PresentationErrorInfo CX_SlidePresenter::checkForPresentationErrors (void) const

Checks the timing data from the last presentation of slides for presentation errors. Currently it checks to see if the intended frame count matches the actual frame count of each slide, which indicates if the furation was correct. It also checks to make sure that the framebuffer was copied to the back buffer before the onset of the slide, which would indicate the potential for vertical tearing.

Returns

A struct with information about the errors that occurred on the last presentation of slides.

Note

If clearSlides() has been called since the end of the presentation, this does nothing as its data has been cleared. If this function is called during slide presentation, the returned struct will have the presentationErrorsSuccessfully-Checked member set to false and an error will be logged.

13.21.3.5 void CX_SlidePresenter::clearSlides (void)

Clears (deletes) all of the slides contained in the slide presenter and stops presentation, if it was in progress.

13.21.3.6 void CX_SlidePresenter::endDrawingCurrentSlide (void)

Ends drawing to the framebuffer of the slide that is currently being drawn to. See beginDrawingNextSlide().

13.21.3.7 std::vector < unsigned int > CX_SlidePresenter::getActualFrameCounts (void)

Gets a vector containing the number of frames that each of the slides from the last presentation of slides was presented for. Note that these frame counts may be wrong. If checkForPresentationErrors() not detect any errors, the frame counts are likely to be right, but there is no guarantee.

Returns

A vector containing the frame counts. The frame count corresponding to the first slide added to the slide presenter will be at index 0.

Note

The frame count of the last slide is meaningless. As far as the slide presenter is concerned, as soon as the last slide is put on the screen, it is done presenting the slides. Because the slide presenter is not responsible for removing the last slide from the screen, it has no idea about the duration of that slide.

13.21.3.8 std::vector < CX Micros > CX SlidePresenter::getActualPresentationDurations (void)

Gets a vector containing the durations of the slides from the last presentation of slides. Note that these durations may be wrong. If checkForPresentationErrors() does not detect any errors, the durations are likely to be right, but there is no guarantee.

Returns

A vector containing the durations. The duration corresponding to the first slide added to the slide presenter will be at index 0.

Note

The duration of the last slide is meaningless. As far as the slide presenter is concerned, as soon as the last slide is put on the screen, it is done presenting the slides. Because the slide presenter is not responsible for removing the last slide from the screen, it has no idea about the duration of that slide.

13.21.3.9 std::vector < CX_SlidePresenter::Slide > & CX_SlidePresenter::getSlides (void)

Get a reference to the vector of slides held by the slide presenter. If you modify any of the members of any of the slides, you do so at your own risk. This data is mostly useful in a read-only sort of way (when was that slide presented?).

Returns

A reference to the vector of slides.

13.21.3.10 bool CX_SlidePresenter::setup (CX Display * display)

Set up the slide presenter with the given CX_Display as the display.

Parameters

display Pointer to the display to use.

Returns

False if there was an error during setup, in which case a message will be logged.

13.21.3.11 bool CX_SlidePresenter::setup (const CX_SlidePresenter::Configuration & config)

Set up the slide presenter using the given configuration.

Parameters

config	The configuration to use.
•	

Returns

False if there was an error during setup, in which case a message will be logged.

```
13.21.3.12 bool CX_SlidePresenter::startSlidePresentation (void)
```

Start presenting the slides that are stored in the slide presenter. After this function is called, calls to update() will advance the state of the slide presentation.

Returns

False if an error was encountered while starting presentation, in which case messages will be logged, true otherwise.

```
13.21.3.13 void CX_SlidePresenter::update(void) [virtual]
```

Updates the state of the slide presenter. If the slide presenter is presenting stimuli, update() must be called very regularly (at least once per millisecond) in order for the slide presenter to function.

The documentation for this class was generated from the following files:

- CX SlidePresenter.h
- CX_SlidePresenter.cpp

13.22 CX::CX SoundObject Class Reference

```
#include <CX_SoundObject.h>
```

Public Member Functions

- bool loadFile (string fileName)
- bool addSound (string fileName, CX_Micros timeOffset)
- bool addSound (CX_SoundObject so, CX_Micros timeOffset)
- bool setFromVector (const std::vector < float > &data, int channels, float sampleRate)
- void clear (void)
- bool isReadyToPlay (void)
- bool isLoadedSuccessfully (void)
- bool applyGain (float gain, int channel=-1)
- bool multiplyAmplitudeBy (float amount, int channel=-1)
- void normalize (float amount=1.0)
- float getPositivePeak (void)
- float getNegativePeak (void)
- void setLength (CX_Micros length)
- CX_Micros getLength (void)
- void stripLeadingSilence (float tolerance)
- void addSilence (CX_Micros duration, bool atBeginning)
- void deleteAmount (CX Micros duration, bool fromBeginning)
- void reverse (void)

- void multiplySpeed (float speedMultiplier)
- void resample (float newSampleRate)
- float getSampleRate (void)

Returns the sample rate of the sound data stored in this CX_SoundObject.

- bool setChannelCount (int channels)
- int getChannelCount (void)

Returns the number of channels in the sound data stored in this CX_SoundObject.

- uint64_t getTotalSampleCount (void)
- uint64_t getSampleFrameCount (void)
- std::vector< float > & getRawDataReference (void)
- bool writeToFile (std::string path)

Public Attributes

· string name

This stores the name of the file from which data was read, if any. It can be set by the user with no side effects.

13.22.1 Detailed Description

This class is a container for a sound. It can load sound files, manipulate the contents of the sound data, add other sounds to an existing sound at specified offsets.

In order to play a CX_SoundObject, you use a CX::CX_SoundObjectPlayer.

See the soundObject example for an introduction on how to use this class along with a CX_SoundObjectPlayer.

Note

Nearly all functions of this class should be considered Blocking Code. Many of the operations take quite a while to complete because they are performed on a potentially large vector of sound samples.

13.22.2 Member Function Documentation

13.22.2.1 void CX_SoundObject::addSilence (CX_Micros duration, bool atBeginning)

Adds the specified amount of silence to the CX_SoundObject at either the beginning or end.

Parameters

duration	Duration of added silence in microseconds. Dependent on the sample rate of the sound. If the
	sample rate changes, so does the duration of silence.
atBeginning	If true, silence is added at the beginning of the CX_SoundObject. If false, the silence is added at
	the end.

13.22.2.2 bool CX_SoundObject::addSound (string fileName, CX_Micros timeOffset)

Uses loadFile(string) and addSound(CX_SoundObject, uint64_t) to add the given file to the current CX_SoundObject at the given time offset (in microseconds). See those functions for more information.

Parameters

fileName	Name of the sound file to load.
timeOffset	Time at which to add the new sound.

Returns

Returns true if the new sound was added sucessfully, false otherwise.

13.22.2.3 bool CX_SoundObject::addSound (CX_SoundObject nso, CX_Micros timeOffset)

Adds the sound data in nso at the time offset. If the sample rates of the sounds differ, nso will be resampled to the sample rate of this CX_SoundObject. If the number of channels of nso does not equal the number of channels of this, an attempt will be made to set the number of channels of nso equal to the number of channels of this CX_SoundObject. The data from nso and this CX_SoundObject are merged by adding the amplitudes of the sounds. The result of the addition is clamped between -1 and 1.

Parameters

nso	A sound object. Must be successfully loaded.
timeOffset	Time at which to add the new sound data in microseconds. Dependent on sample rate.

Returns

True if nso was successfully added to this CX SoundObject, false otherwise.

13.22.2.4 bool CX_SoundObject::applyGain (float decibels, int channel = -1)

Apply gain to the channel in terms of decibels.

Parameters

ſ	decibels	Gain to apply. 0 does nothing. Positive values increase volume, negative values decrease
		volume. Negative infinity is essentially mute, although see multiplyAmplitudeBy() for a more
		obvious way to do that same operation.
Ì	channel	The channel that the gain should be applied to. If channel is less than 0, the gain is applied to all
		channels.

13.22.2.5 void CX_SoundObject::clear (void)

Clears all data stored in the sound object and returns it to an uninitialized state.

13.22.2.6 void CX_SoundObject::deleteAmount (CX_Micros duration, bool fromBeginning)

Deletes the specified amount of sound from the CX SoundObject from either the beginning or end.

Parameters

duration	Duration of removed sound in microseconds. If this is greater than the duration of the sound, the
	whole sound is deleted.
fromBeginning	If true, sound is deleted from the beginning of the CX_SoundObject's buffer. If false, the sound
	is deleted from the end, toward the beginning.

13.22.2.7 CX_Micros CX_SoundObject::getLength (void)

Gets the length, in time, of the sound object.

Returns

The length.

13.22.2.8 float CX_SoundObject::getNegativePeak (void)

Finds the minimum amplitude in the sound object.

Returns

The minimum amplitude.

Note

Amplitudes are between -1 and 1, inclusive.

13.22.2.9 float CX_SoundObject::getPositivePeak (void)

Finds the maximum amplitude in the sound object.

Returns

The maximum amplitude.

Note

Amplitudes are between -1 and 1, inclusive.

13.22.2.10 std::vector<float>& CX::CX_SoundObject::getRawDataReference (void) [inline]

This function returns a reference to the raw data underlying the sound object.

Returns

A reference to the data. Modify at your own risk!

```
13.22.2.11 uint64_t CX::CX_SoundObject::getSampleFrameCount(void) [inline]
```

This function returns the number of sample frames in the sound data held by the CX_SoundObject, which is equal to the total number of samples divided by the number of channels.

```
13.22.2.12 uint64_t CX::CX_SoundObject::getTotalSampleCount(void) [inline]
```

This function returns the total number of samples in the sound data held by the CX_SoundObject, which is equal to the number of sample frames times the number of channels.

```
13.22.2.13 bool CX::CX_SoundObject::isLoadedSuccessfully(void) [inline]
```

Checks to see if sound data has been successfully loaded into this CX_SoundObject from a file.

```
13.22.2.14 bool CX_SoundObject::isReadyToPlay ( void )
```

Checks to see if the CX_SoundObject is ready to play. It basically just checks if there is sound data available and that the number of channels is set to a sane value.

13.22.2.15 bool CX_SoundObject::loadFile (string fileName)

Loads a sound file with the given file name into the CX_SoundObject. Any pre-existing data in the sound object is deleted. Some sound file types are supported. Others are not. In the limited testing, mp3 and wav files seem to work well. If the file cannot be loaded, descriptive error messages will be logged.

Parameters

fileName	Name of the sound file to load.

Returns

True if the sound given in the fileName was loaded succesffuly, false otherwise.

13.22.2.16 bool CX_SoundObject::multiplyAmplitudeBy (float amount, int channel = -1)

Apply gain to the sound. The original value is simply multiplied by the amount and then clamped to be within [-1, 1].

Parameters

amount	The gain that should be applied. A value of 0 mutes the channel. 1 does nothing. 2 doubles the amplitude1 inverts the waveform.
channel	The channel that the given multiplier should be applied to. If channel is less than 0, the amplitude
	multiplier is applied to all channels.

13.22.2.17 void CX_SoundObject::multiplySpeed (float speedMultiplier)

This function changes the speed of the sound by some multiple.

Parameters

speedMultiplier	Amount to multiply the speed by. Must be greater than 0.
-----------------	--

Note

If you would like to use a negative value to reverse the direction of playback, see reverse().

13.22.2.18 void CX_SoundObject::normalize (float amount = 1.0)

Normalizes the contents of the sound object.

Parameters

the greatest magnitude will be set to +/-1 and everything else will be scaled relative to the peak.
If amount is less than 1, the greatest peak will be set to that value.

13.22.2.19 void CX_SoundObject::resample (float newSampleRate)

Resamples the audio data stored in the CX_SoundObject by linear interpolation. Linear interpolation is not the ideal way to resample audio data; some audio fidelity is lost, more so than with other resampling techinques. It is, however, very fast compared to higher-quality methods both in terms of run time and programming time. It has acceptable results, at least when the new sample rate is similar to the old sample rate.

Parameters

newSampleRate	The requested sample rate.

13.22.2.20 void CX_SoundObject::reverse (void)

This function reverses the sound data stored in the CX SoundObject so that if it is played, it will play in reverse.

13.22.2.21 bool CX_SoundObject::setChannelCount (int newChannelCount)

Sets the number of channels of the sound. Depending on the old number of channels (N) and the new number of channels (M), the conversion is performed in different ways. If N = M, nothing happens. If N = 1, each of the M new channels is set equal to the value of the single old channel. If M = 1, the new channel is set equal to the arithmetic average of the N old channels. If (N != 1 && M != 1 && M > N), the first N channels are preserved unchanged and the M - N new channels are set to the arithmetic average of the N old channels. Any other combination of M and N is an error condition.

Parameters

newChannel-	The number of channels the CX_SoundObject will have after the conversion.
Count	

Returns

True if the conversion was successful, false if the attempted conversion is unsupported.

13.22.2.22 bool CX_SoundObject::setFromVector (const std::vector < float > & data, int channels, float sampleRate)

Set the contents of the sound object from a vector of float data.

Parameters

data	A vector of sound samples. These values should go from -1 to 1. This requirement is not checked
	for. If there is more than once channel of data, the data must be interleaved. This means that
	if, for example, there are two channels, the ordering of the samples is 12121212 where 1
	represents a sample for channel 1 and 2 represents a sample for channel 2. This requirement is
	not checked for. The number of samples in this vector must be evenly divisible by the number of
	channels set with the channels argument.
channels	The number of channels worth of data that is stored in data.
sampleRate	The sample rate of the samples. If data contains, for example, a sine wave, that wave was
	sampled at some rate (e.g. 48000 samples per second of waveform). sampleRate should be
	that rate. return True in all cases. No checking is done on any of the arguments.

13.22.2.23 void CX_SoundObject::setLength (CX_Micros length)

Set the length of the sound to the specified length in microseconds. If the new length is longer than the old length, the new data is zeroed (i.e. set to silence).

13.22.2.24 void CX_SoundObject::stripLeadingSilence (float tolerance)

Removes leading "silence" from the sound, where silence is defined by the given tolerance. It is unlikely that the beginning of a sound, even if perceived as silent relative to the rest of the sound, has an amplitude of 0. Therefore, a tolerance of 0 is unlikely to prove useful. Using getPositivePeak() and/or getNegativePeak() can help to give a reference amplitude of which some small fraction is perceived as "silent".

Parameters

tolerance	All sound data up to and including the first instance of a sample with an amplitude with an
	absolute value greater than or equal to tolerance is removed from the sound.

13.22.2.25 bool CX_SoundObject::writeToFile (std::string filename)

Writes the contents of the sound object to a file with the given file name. The data will be encoded as 16-bit PCM. The sample rate is determined by the sample rate of the sound object.

Parameters

filename	The name of the file to save the sound data to. filename should have a .wav extension. If it
	does not, ".wav" will be appended to the file name and a warning will be logged.

Returns

False if there was an error while opening the file. If so, an error will be logged.

The documentation for this class was generated from the following files:

- · CX_SoundObject.h
- CX_SoundObject.cpp

13.23 CX::CX_SoundObjectPlayer Class Reference

#include <CX_SoundObjectPlayer.h>

Public Member Functions

- bool setup (CX_SoundObjectPlayerConfiguration_t config)
- bool play (void)
- bool startPlayingAt (CX Micros experimentTime, CX Micros offset)
- bool stop (void)
- bool isPlaying (void)

Check if the sound is currently playing.

bool isQueuedToStart (void)

Check if the sound is queued to play.

CX_SoundObjectPlayerConfiguration_t getConfiguration (void)

Returns the configuration used for this CX_SoundObjectPlayer.

- bool BLOCKING_setSound (CX_SoundObject *sound)
- void setTime (CX_Micros time)

13.23.1 Detailed Description

This class is used for playing CX_SoundObjects. See the soundObject example for an example of how to use this class.

13.23.2 Member Function Documentation

13.23.2.1 bool CX SoundObjectPlayer::BLOCKING setSound (CX SoundObject * sound)

This function is blocking because the sample rate and number of channels of sound are changed to those of the currently open stream.

Parameters

sound	A pointer to a CX_SoundObject that will be set as the current sound for the CX_SoundObject-
	Player. There are a variety of reasons why the sound could fail to be set as the current sound for
	the player. If sound was not loaded successfully, this function call fails and an error is logged. If
	it is not possible to convert the number of channels of sound to the number of channels that the
	CX_SoundObjectPlayer is configured to use, this function call fails and an error is logged.

This function call is not blocking if the same rate and channel count of the CX_SoundObject are the same as those in use by the CX_SoundObjectPlayer. See Blocking Code for more information.

Returns

True if sound was successfully set to be the current sound, false otherwise.

13.23.2.2 bool CX_SoundObjectPlayer::play (void)

Attempts to start playing the current CX_SoundObject associated with the player.

Returns

True if the sound object associated with the player is ReadyToPlay(), false otherwise.

13.23.2.3 void CX_SoundObjectPlayer::setTime (CX_Micros time)

Set the current time in the active sound. When playback starts, it will begin from that time in the sound. If the sound object is currently playing, this will jump to that point in the sound.

Parameters

time	The time in the sound to seek to.
------	-----------------------------------

13.23.2.4 bool CX_SoundObjectPlayer::setup (CX_SoundObjectPlayerConfiguration_t config)

Configures the CX_SoundObjectPlayer with the given configuration.

13.23.2.5 bool CX_SoundObjectPlayer::startPlayingAt (CX_Micros experimentTime, CX_Micros latencyOffset)

Queue the start time of the sound in experiment time with an offset to account for latency.

Parameters

experimentTime	The desired experiment time at which the sound should start playing. This time plus the offset
	should be in the future. If it is not, the sound will start playing immediately.
latencyOffset	An offset that accounts for latency. If, for example, you called this function with an offset of 0 and
	discovered that the sound played 200 ms later than you were expecting it to, you would set offset
	to -200 * 1000 in order to queue the start time 200 ms earlier than the desired experiment time.

Returns

False if the start time plus the offset is in the past. True otherwise.

Note

See setTime() for a way to choose the current time point within the sound.

```
13.23.2.6 bool CX_SoundObjectPlayer::stop ( void )
```

Stop the currently playing sound object, or, if a playback start was cued, cancel the cued playback.

Returns

Always returns true currently.

The documentation for this class was generated from the following files:

- · CX_SoundObjectPlayer.h
- CX_SoundObjectPlayer.cpp

13.24 CX::CX_SoundObjectRecorder Class Reference

```
#include <CX_SoundObjectRecorder.h>
```

Public Types

· typedef

CX_SoundStream::Configuration Configuration

This is typedef'ed to CX::CX_SoundStream::Configuration.

Public Member Functions

- bool setup (CX_SoundObjectRecorder::Configuration &config)
- void setSoundObject (CX SoundObject *so)
- CX_SoundObject * getSoundObject (void)
- void startRecording (bool clearExistingData=false)
- · void stopRecording (void)

13.24.1 Detailed Description

This class is used for recording audio data from, e.g., a microphone. The recorded data is stored in a CX_SoundObject for further use.

```
CX_SoundObjectRecorder::Configuration recorderConfig;
recorderConfig.inputChannels = 1; //You will probably need to configure more than just this
recorder.setup(recorderConfig);

CX_SoundObject recording;
recorder.setSoundObject(&recording); //Associate a CX_SoundObject with the recorder so that it can be
    recorded to.

//Record for 5 seconds
recorder.startRecording();
ofSleepMillis(5000);
recorder.stopRecording();
//Write the recording to a file
recording.writeToFile("recording.wav");
```

13.24.2 Member Function Documentation

13.24.2.1 CX SoundObject * CX_SoundObjectRecorder::getSoundObject (void)

This function returns a pointer to the CX_SoundObject that is currently associated with this CX_SoundObjectRecorder.

13.24.2.2 void CX_SoundObjectRecorder::setSoundObject ($CX_SoundObject*so$)

This function associates a CX_SoundObject with the CX_SoundObjectRecorder. The CX_SoundObject will be recorded to when startRecording() is called.

Parameters

so	The CX_SoundObject to associate with the CX_SoundObjectRecorder. The sound object will be
	cleared and it will be configured to have the same number of channels and sample rate that the
	CX_SoundObjectRecorder was configured to use.

13.24.2.3 bool CX_SoundObjectRecorder::setup (CX_SoundObjectRecorder::Configuration & config)

This function sets up the CX_SoundStream that CX_SoundObjectRecorder uses to record audio data.

Returns

True if configuration of the CX_SoundStream was successful, false otherwise.

13.24.2.4 void CX_SoundObjectRecorder::startRecording (bool clearExistingData = false)

Begins recording data to the CX_SoundObject that was associated with this CX_SoundObjectRecorder with setSoundObject().

Parameters

clearExistingData If true, any data in the CX_SoundObject will be deleted before recording starts.

13.24.2.5 void CX_SoundObjectRecorder::stopRecording (void)

Stop recording sound data.

The documentation for this class was generated from the following files:

- · CX SoundObjectRecorder.h
- CX_SoundObjectRecorder.cpp

13.25 CX::CX_SoundStream Class Reference

#include <CX_SoundStream.h>

Classes

- struct Configuration
- struct InputEventArgs
- struct OutputEventArgs

Public Member Functions

- bool setup (CX SoundStream::Configuration &config)
- · bool closeStream (void)
- bool start (void)
- bool stop (void)
- · const

CX_SoundStream::Configuration & getConfiguration (void)

- uint64_t getSampleFrameNumber (void)
- CX Micros getStreamLatency (void)
- bool hasSwappedSinceLastCheck (void)
- CX_Micros getLastSwapTime (void)
- CX Micros estimateNextSwapTime (void)
- RtAudio * getRtAudioInstance (void)

Static Public Member Functions

- static std::vector< RtAudio::Api > getCompiledApis (void)
- static std::vector < std::string > convertApisToStrings (vector < RtAudio::Api > apis)
- static std::string convertApisToString (vector < RtAudio::Api > apis, std::string delim="\r\n")
- static std::string convertApiToString (RtAudio::Api api)
- static std::vector< std::string > **formatsToStrings** (RtAudioFormat formats)
- static std::string formatsToString (RtAudioFormat formats, std::string delim="\r\n")
- static std::vecto
 - < RtAudio::DeviceInfo > getDeviceList (RtAudio::Api api)
- static std::string listDevices (RtAudio::Api api)

Public Attributes

- ofEvent
 - < CX SoundStream::OutputEventArgs > outputEvent

This event is triggered every time the CX_SoundStream needs to feed more data to the output buffer of the sound card.

- ofEvent
 - < CX SoundStream::InputEventArgs > inputEvent

This event is triggered every time the CX SoundStream hsa gotten some data from the input buffer of the sound card.

13.25.1 Detailed Description

This class provides a method for directly accessing and manipulating sound data that is sent/received from sound hardware. To use this class, you should set up the stream (see setup()), set a user function that will be called when either the outputEvent or inputEvent is triggered, and start the stream with start().

If the stream in configured for output, the output event will be triggered whenever the sound card needs more sound data. If the stream is configured for input, the input event will be triggered whenever some amount of sound data has been recorded.

CX_SoundStream uses RtAudio internally, so you are having problems, you might be able to figure out what is going wrong by checking out the page for RtAudio: http://www.music.mcgill.ca/~gary/rtaudio/index.-html

13.25.2 Member Function Documentation

13.25.2.1 bool CX_SoundStream::closeStream (void)

Closes the sound stream.

Returns

False if an error was encountered while closing the stream, true otherwise.

```
13.25.2.2 std::string CX_SoundStream::convertApisToString ( vector < RtAudio::Api > apis, std::string delim = "\r" ) [static]
```

This helper function converts a vector of RtAudio::Api to a string, with the specified delimiter between API names.

Parameters

apis	The vector of RtAudio::Api to convert to string.
delim	The delimiter between elements of the string.

Returns

A string containing the names of the APIs.

13.25.2.3 std::vector< std::string > CX_SoundStream::convertApisToStrings (vector< RtAudio::Api > apis) [static]

This helper function converts a vector of RtAudio::Api to a vector of strings, using convertApiToString() for the conversion. Parameters

apis	A vector of apis to convert to strings.

Returns

A vector of string names of the apis.

13.25.2.4 std::string CX SoundStream::convertApiToString (RtAudio::Api api) [static]

This helper function converts an RtAudio::Api to a string.

Parameters

api	The api to get a string of.

Returns

A string of the api name.

13.25.2.5 CX_Micros CX_SoundStream::estimateNextSwapTime (void)

Estimate the time at which the next buffer swap will occur.

Returns

The estimated time of next swap. This value can be compared with the result of CX::Instances::Clock.getTime().

```
13.25.2.6 std::vector < RtAudio::Api > CX_SoundStream::getCompiledApis(void) [static]
```

Get a vector containing a list of all of the APIs for which the RtAudio driver has been compiled to use. If the API you want is not available, you might be able to get it by using a different version of RtAudio.

```
13.25.2.7 const CX SoundStream::Configuration& CX::CX SoundStream::getConfiguration(void) [inline]
```

Gets the configuration that was used on the last call to open(). Because some of the configuration options are only suggestions, this function allows you to check what the actual configuration was.

Returns

A const reference to the configuration struct.

```
13.25.2.8 std::vector < RtAudio::DeviceInfo > CX SoundStream::getDeviceList ( RtAudio::Api api ) [static]
```

For the given api, lists all of the devices on the system that support that api.

Parameters

api	Devices that support this API are scanned.
-----	--

Returns

A machine-readable list of information. See http://www.music.mcgill.ca/~gary/rtaudio/struct-RtAudio 1 1DeviceInfo.html for information about the members of the RtAudio::DeviceInfo struct.

```
13.25.2.9 CX_Micros CX::CX_SoundStream::getLastSwapTime(void) [inline]
```

Gets the time at which the last buffer swap occurred.

Returns

This time value can be compared with the result of CX::Instances::Clock.getTime().

```
13.25.2.10 RtAudio * CX_SoundStream::getRtAudioInstance ( void )
```

This function returns a pointer to the RtAudio instance that this CX_SoundStream is using. This should not be needed most of the time, but there may be cases in which you need to directly access RtAudio. Here is the documentation for RtAudio: https://www.music.mcgill.ca/~gary/rtaudio/

```
13.25.2.11 uint64_t CX::CX SoundStream::getSampleFrameNumber(void) [inline]
```

Returns the number of the sample frame that

```
13.25.2.12 CX_Micros CX_SoundStream::getStreamLatency (void)
```

This function gets an estimate of the stream latency. However, it should not be relied on as it is based on what the sound card driver reports, which is often false.

Returns

The stream latency in microseconds.

```
13.25.2.13 bool CX_SoundStream::hasSwappedSinceLastCheck (void)
```

This function checks to see if the audio buffers have been swapped since the last time this function was called.

Returns

True if at least one audio buffer has been swapped out, false if no buffers have been swapped.

```
13.25.2.14 std::string CX_SoundStream::listDevices ( RtAudio::Api api ) [static]
```

For the given api, lists all of the devices on the system that support that api. Lots of information about each device is given, like supported sample rates, number of input and output channels, etc.

Parameters

api	Devices that support this API are scanned.
αρι	Devices that support this Arrare scanned.

Returns

A human-readable formatted string containing the scanned information. Can be printed directly to std::cout or elsewhere.

13.25.2.15 bool CX_SoundStream::setup (CX_SoundStream::Configuration & config)

Opens the sound stream with the specified configuration. If there was an error during configuration, messages will be logged.

Parameters

config	The configuration settings that are desired. Some of the configuration options are only sugges-
	tions, so some of the values that are used may differ from the values that are chosen. In those
	cases, config is updated based on the actually used settings. You can check the configuration
	later using getConfiguration().

Returns

True if configuration appeared to be successful, false otherwise.

Note

Opening the stream does not start it. See start().

13.25.2.16 bool CX_SoundStream::start (void)

Starts the sound stream. The stream must already be open().

Returns

False if the stream was not started, true if the stream was started or if it was already running.

13.25.2.17 bool CX_SoundStream::stop (void)

Stop the stream, if is running. If there is an error, a message will be logged.

Returns

False if there was an error, true otherwise.

The documentation for this class was generated from the following files:

- · CX SoundStream.h
- CX SoundStream.cpp

13.26 CX::Util::CX_TrialController Class Reference

```
#include <CX_TrialController.h>
```

Public Member Functions

- int update (void)
- · void start (void)

"Arm" the trial controller. Before this is called, update() will do nothing.

void stop (void)

"Disarm" the trial controller. After this is called, update() will do nothing.

bool isActive (void)

Check to see if the trial controller is active. See start() and stop().

- void appendFunction (std::function < int(void) > userFunction)
- · void reset (void)
- bool setCurrentFunction (int currentFunction)
- int getCurrentFunction (void)

Get the index of the current function (i.e. the function that will be called the next time update() is called).

unsigned int getFunctionCount (void)

Get the number of user functions stored by this trial controller.

13.26.1 Detailed Description

This class is used to help with the fact that most psychology experiments are by nature more or less linear, but that CX works better if code does not block (see Blocking Code).

The way this works is that segments of user code, each representing one part of a trial, are put into functions. Those functions are added to the trial controller with appendFunction(), which puts the function at the end of the list of functions. User functions take no arguments and return an int.

When you want to use the trial controller, call start() and it will be "armed". When it is armed and update() is called, it will call the current function in the list of user functions. If the user function is done with whatever it needs to do, it should return 1. This will cause the trial controller to move on to the next user function. If the user function is not done with its task, it should return 0. If it returns 0, it will be called again the next time update() is called.

13.26.2 Member Function Documentation

 $13.26.2.1 \quad \text{void CX_TrialController::appendFunction (std::function} < \text{int(void)} > \textit{userFunction })$

Adds a user function to the end of the list of functions to be called by the trial controller.

Parameters

userFunction	Typically a pointer to a function that takes no arguments and returns an int. Because it is a
	std::function, it can also be a lamda.

13.26.2.2 void CX_TrialController::reset (void)

Clear the user functions and otherwise reset to default state.

Note

This function stops the trial controller (isActive() will return false).

13.26.2.3 bool CX_TrialController::setCurrentFunction (int currentFunction)

Sets the current user function by index, which allows you to skip over functions or go back to a previous function.

Parameters

currentFunction	The new current function index. If this is out of range, an error will be logged and the function
	will return false.

Returns

False if the index was out of range, true otherwise.

Note

If this is called from within a user function that has been called from this instance of the CX_TrialController, that function should return 0. If it does not, setCurrentFunction() will set the function index and then that index will be incremented after the user function completes. However, if 0 is returned, the function index is not incremented.

13.26.2.4 int CX_TrialController::update (void)

Updates the trial controller state. Each time this function is called, the user function at the current function index is called. If that function returns a nonzero value, the trial controller will increment the current function index and that function will be called the next time update() is called. If the current function index is incremented past the end of the list of functions, it will wrap around to the beginning of the list.

Returns

The value returned by the user function that was called.

Note

This function should probably be called every time updateExperiment() is called, although there are other use cases.

If not isActive(), this function does nothing and returns 0.

The documentation for this class was generated from the following files:

- · CX_TrialController.h
- · CX_TrialController.cpp

13.27 CX::Synth::Envelope Class Reference

```
#include <CX_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Member Functions

- double getNextSample (void) override
- · void attack (void)
- void release (void)

Public Attributes

- · double a
- · double d
- double s
- double r

Additional Inherited Members

13.27.1 Detailed Description

This class is an ADSR envelope: http://en.wikipedia.org/wiki/Synthesizer#ADSR_envelope Setting the a, d, s, and r parameters works in the standard way. s should be in the interval [0,1]. a, d, and r are expressed in seconds. Call attack() to start the envelope. Once the attack and decay are finished, the envelope will stay at the sustain level until release() is called.

13.27.2 Member Function Documentation

```
13.27.2.1 double Envelope::getNextSample(void) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- · CX ModularSynth.h
- CX_ModularSynth.cpp

13.28 CX::CX_Mouse::Event Struct Reference

```
#include <CX_Mouse.h>
```

Public Types

enum MouseEventType {
 MOVED, PRESSED, RELEASED, DRAGGED,
 SCROLLED }

Public Attributes

int button

The relevant mouse button if the eventType is PRESSED, RELEASED, or DRAGGED. Can be compared with elements of enum CX_MouseButtons to find out about the primary buttons.

int x

The x position of the cursor at the time of the event, or the change in the x-axis scroll if the eventType is SCROLLED.

int y

The y position of the cursor at the time of the event, or the change in the y-axis scroll if the eventType is SCROLLED.

CX Micros eventTime

The time at which the event was registered. Can be compared to the result of CX::Clock::getTime().

CX Micros uncertainty

The uncertainty in eventTime. The event occured some time between eventTime and eventTime minus uncertainty.

enum

CX::CX_Mouse::Event::MouseEventType eventType

The type of the event.

13.28.1 Detailed Description

This struct contains the results of a mouse event, which is any type of interaction with the mouse, be it simply movement, a button press or release, a drag event (mouse button held while mouse is moved), or movement of the scroll wheel.

13.28.2 Member Enumeration Documentation

13.28.2.1 enum CX::CX Mouse::Event::MouseEventType

Enumerator

MOVED The mouse has been moved without a button being held. button should be -1 (meaningless).

PRESSED A mouse button has been pressed. Check button for the button index and x and y for the location.

RELEASED A mouse button has been released. Check button for the button index and x and y for the location.

DRAGGED can be changed during a drag, or multiple buttons may be held at once during a drag. The mouse has been moved while at least one button was held. button may not be meaningful because the held button

SCROLLED mouse has a wheel that can move horizontally. The mouse wheel has been scrolled. Check y to get the change in the standard mouse wheel, or x if your

The documentation for this struct was generated from the following file:

· CX Mouse.h

13.29 CX::CX_Joystick::Event Struct Reference

#include <CX_Joystick.h>

Public Types

enum JoystickEventType { BUTTON PRESS, BUTTON RELEASE, AXIS POSITION CHANGE }

Public Attributes

int buttonIndex

If eventType is BUTTON_PRESS or BUTTON_RELEASE, this contains the index of the button that was changed.

• unsigned char buttonState

If eventType is BUTTON_PRESS or BUTTON_RELEASE, this contains the current state of the button.

int axisIndex

If eventType is AXIS_POSITION_CHANGE, this contains the index of the axis which changed.

float axisPosition

If eventType is AXIS POSITION CHANGE, this contains the amount by which the axis changed.

CX Micros eventTime

The time at which the event was registered. Can be compared to the result of CX::Clock::getTime().

CX Micros uncertainty

The uncertainty in eventTime. The event occured some time between eventTime and eventTime minus uncertainty.

• enum

CX::CX_Joystick::Event::JoystickEventType eventType

The type of the event.

13.29.1 Detailed Description

This struct contains information about joystick events. Joystick events are either a button press or release or a change in the axes of the joystick.

13.29.2 Member Enumeration Documentation

13.29.2.1 enum CX::CX_Joystick::Event::JoystickEventType

Enumerator

BUTTON_PRESS A button on the joystick has been pressed. See buttonIndex and buttonState for the event data.

BUTTON_RELEASE A button on the joystick has been released. See buttonIndex and buttonState for the event data.

AXIS_POSITION_CHANGE The joystick has been moved in one of its axes. See axisIndex and axisPosition for the event data.

The documentation for this struct was generated from the following file:

· CX_Joystick.h

13.30 CX::CX_Keyboard::Event Struct Reference

#include <CX_Keyboard.h>

Public Types

enum KeyboardEventType { PRESSED, RELEASED, REPEAT }

Public Attributes

- int key
- CX Micros eventTime

The time at which the event was registered. Can be compared to the result of CX::Clock::getTime().

CX Micros uncertainty

The uncertainty in eventTime. The event occured some time between eventTime and eventTime minus uncertainty.

enum

CX::CX Keyboard::Event::KeyboardEventType eventType

The type of the event.

13.30.1 Detailed Description

This struct contains the results of a keyboard event, whether it be a key press or release, or key repeat.

13.30.2 Member Enumeration Documentation

13.30.2.1 enum CX::CX Keyboard::Event::KeyboardEventType

Enumerator

PRESSED A key has been pressed.

RELEASED A key has been released.

REPEAT A key has been held for some time and automatic key repeat has kicked in, causing multiple keypresses to be rapidly sent. This event is one of the many repeats.

13.30.3 Member Data Documentation

13.30.3.1 int CX::CX_Keyboard::Event::key

The key involved in this event. The value of this can be compared with character literals for many of the standard keyboard keys. For example, you could use '(myKeyEvent.key == 'e')' to test if the key was the E key. Note that if shift is held when the key is pressed, the letter will be uppercase, so you may want to check for both 'e' and 'E'.

For special keys, key can be compared with the key constant values defined in of Constants.h (e.g. OF_KEY_ESC).

Note that for the modifier keys (shift, ctrl, alt, and super) are treated a little unusually. For those keys, you can check for a specific key using, for example, OF_KEY_RIGHT_CONTROL or OF_KEY_LEFT_CONTROL. However, you can alternately check to see if key is any of the control keys by performing a bitwise AND with OF_KEY_CONTROL and checking that the result of the AND is still OF_KEY_CONTROL. For example:

```
if ((myKeyEvent.key & OF_KEY_CONTROL) == OF_KEY_CONTROL) {
//...
}
```

This works the same way for all of the modifier keys.

The documentation for this struct was generated from the following file:

· CX_Keyboard.h

13.31 CX::CX_SlidePresenter::FinalSlideFunctionArgs Struct Reference

#include <CX_SlidePresenter.h>

Public Attributes

CX SlidePresenter * instance

A pointer to the CX_SlidePresenter that called the user function.

· unsigned int currentSlideIndex

The index of the slide that is currently being presented.

13.31.1 Detailed Description

The final slide function takes a reference to a struct of this type.

The documentation for this struct was generated from the following file:

· CX SlidePresenter.h

13.32 CX::Synth::FIRFilter Class Reference

```
#include <CX_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Types

- enum FilterType { LOW_PASS, HIGH_PASS, USER_DEFINED }
- enum WindowType { RECTANGULAR, HANNING, BLACKMAN }

Public Member Functions

- void **setup** (FilterType filterType, unsigned int coefficientCount)
- void setup (std::vector< double > coefficients)
- void setCutoff (double cutoff)
- double getNextSample (void)

Additional Inherited Members

13.32.1 Detailed Description

This class is a start at implementing a Finite Impulse Response (http://en.wikipedia.org/wiki/Finite__impulse_response) filter. You can use it as a basic low-pass or high-pass filter, or, if you supply your own coefficients, which cause the filter to do filtering in whatever way you want. See the "signal" package for R for a method of constructing your own coefficients.

13.32.2 Member Function Documentation

```
13.32.2.1 double CX::Synth::FIRFilter::getNextSample(void) [inline], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following file:

· CX_ModularSynth.h

13.33 CX::CX SoundStream::InputEventArgs Struct Reference

```
#include <CX_SoundStream.h>
```

Public Attributes

bool bufferOverflow

This is set to true if there was a buffer overflow, which means that the sound hardware recorded data that was not processed.

float * inputBuffer

A pointer to an array of sound data that should be processed by the event handler function.

· unsigned int bufferSize

The number of sample frames that are in inputBuffer. The total number of samples is bufferSize * input-Channels.

· int inputChannels

The number of channels worth of data in inputBuffer.

CX_SoundStream * instance

A pointer to the CX_SoundStream instance that contains the input event.

13.33.1 Detailed Description

The audio input event of the CX_SoundStream sends a copy of this structure with the fields filled out when the event is called.

The documentation for this struct was generated from the following file:

· CX SoundStream.h

13.34 CX::Synth::Mixer Class Reference

```
#include <CX_ModularSynth.h>
Inherits CX::Synth::ModuleBase.
```

Public Member Functions

double getNextSample (void) override

Additional Inherited Members

13.34.1 Detailed Description

This class mixes together a number of inputs. It does no mixing in the usual sense of setting levels of the inputs. Use Multipliers on the inputs for that. This class simply adds together all of the inputs with no amplitude correction, so it is possible for the output of the mixer to have very large amplitudes.

This class is special in that it can have more than one input.

13.34.2 Member Function Documentation

```
13.34.2.1 double Mixer::getNextSample (void ) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- · CX ModularSynth.h
- CX_ModularSynth.cpp

13.35 CX::Synth::ModuleBase Class Reference

```
#include <CX_ModularSynth.h>
```

Inherited by CX::Synth::Adder, CX::Synth::AdditiveSynth, CX::Synth::Clamper, CX::Synth::Envelope, CX::Synth::FIR-Filter, CX::Synth::GenericOutput, CX::Synth::Mixer, CX::Synth::Multiplier, CX::Synth::Oscillator, CX::Synth::RCFilter, CX::Synth::RecursiveFilter, CX::Synth::SoundObjectInput, CX::Synth::Splitter, CX::Synth::StreamOutput, and CX::Synth::TrivialGenerator.

Public Member Functions

- virtual double getNextSample (void)
- void setData (ModuleControlData t d)
- ModuleControlData_t getData (void)

Protected Member Functions

- virtual void _dataSetEvent (void)
- void _dataSet (ModuleBase *caller)
- void _setDatalfNotSet (ModuleBase *target)
- void _registerParameter (ModuleParameter *p)
- virtual void _assignInput (ModuleBase *in)
- virtual void _assignOutput (ModuleBase *out)
- virtual int _maxInputs (void)
- virtual int _maxOutputs (void)
- virtual void _inputAssignedEvent (ModuleBase *in)
- virtual void _outputAssignedEvent (ModuleBase *out)

Protected Attributes

- vector< ModuleBase * > _inputs
- vector< ModuleBase * > _outputs
- vector< ModuleParameter * > _parameters
- ModuleControlData_t * _data

Friends

ModuleBase & operator>> (ModuleBase &I, ModuleBase &r)

13.35.1 Detailed Description

All modules of the modular synth inherit from this class.

13.35.2 Member Function Documentation

```
13.35.2.1 virtual double CX::Synth::ModuleBase::getNextSample(void) [inline], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented in CX::Synth::RCFilter, CX::Synth::RecursiveFilter, CX::Synth::FIRFilter, CX::Synth::Oscillator, CX::Synth::SoundObjectInput, CX::Synth::Splitter, CX::Synth::Mixer, CX::Synth::Mixer, CX::Synth::Envelope, CX::Synth::Clamper, CX::Synth::Adder, and CX::Synth::AdditiveSynth.

```
13.35.2.2 void CX::Synth::ModuleBase::setData ( ModuleControlData t d ) [inline]
```

This function sets the data needed by this module in order to function properly. Many modules need this data, specifically the sample rate that the synth using. If several modules are connected together, you will only need to set the data for one module and the change will propagate to the other connected modules automatically.

This function does not usually need to be called driectly by the user. If an appropriate input or output is connected, the data will be set from that module.

Parameters

```
d The data to set.
```

13.35.3 Friends And Related Function Documentation

```
13.35.3.1 ModuleBase&operator>>( ModuleBase&r) [friend]
```

This operator is used to connect modules together. 1 is set as the input for r.

```
Oscillator osc;
StreamOutput out;
osc >> out; //Connect osc as the input for out.
```

The documentation for this class was generated from the following files:

- · CX ModularSynth.h
- CX_ModularSynth.cpp

13.36 CX::Synth::Multiplier Class Reference

```
#include <CX_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Member Functions

- double getNextSample (void) override
- void setGain (double decibels)

Public Attributes

ModuleParameter amount

Additional Inherited Members

13.36.1 Detailed Description

This class multiplies an input by an amount. You can set the amount in terms of decibels of gain by using the setGain() function.

13.36.2 Member Function Documentation

```
13.36.2.1 double Multiplier::getNextSample(void) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

13.36.2.2 void Multiplier::setGain (double decibels)

Sets the amount of the multiplier based on gain in decibels.

Parameters

decibels	The gain to apply. If greater than 0, amount will be greater than 1. If less than 0, amount will
	be less than 1. After calling this function, amount will never be negative.

The documentation for this class was generated from the following files:

- · CX_ModularSynth.h
- CX_ModularSynth.cpp

13.37 CX::Synth::Oscillator Class Reference

```
#include <CX_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Member Functions

- double getNextSample (void) override
- void setGeneratorFunction (std::function< double(double)> f)

Static Public Member Functions

- static double saw (double wp)
- static double sine (double wp)
- static double **square** (double wp)
- static double **triangle** (double wp)
- static double whiteNoise (double wp)

Public Attributes

ModuleParameter frequency

Additional Inherited Members

13.37.1 Detailed Description

This class provides one of the simplest ways of generating waveforms.

```
//Configure the oscillator to produce a square wave with a fundamental frequency of 200 Hz.
Oscillator osc;
osc.frequency = 200;
osc.setGeneratorFunction(Oscillator::square);
```

13.37.2 Member Function Documentation

```
13.37.2.1 double Oscillator::getNextSample ( void ) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- · CX ModularSynth.h
- CX_ModularSynth.cpp

13.38 CX::CX SoundStream::OutputEventArgs Struct Reference

```
#include <CX_SoundStream.h>
```

Public Attributes

bool bufferUnderflow

This is set to true if there was a buffer underflow, which means that the sound hardware ran out of data to output.

float * outputBuffer

A pointer to an array that should be filled with sound data.

unsigned int bufferSize

The number of sample frames that are in outputBuffer. The total number of samples is bufferSize * output-Channels.

· int outputChannels

The number of channels worth of data in outputBuffer.

CX_SoundStream * instance

A pointer to the CX_SoundStream instance that contains the output event.

13.38.1 Detailed Description

The audio output event of the CX_SoundStream sends a copy of this structure with the fields filled out when the event is called.

The documentation for this struct was generated from the following file:

· CX SoundStream.h

13.39 CX::CX_SlidePresenter::PresentationErrorInfo Struct Reference

```
#include <CX_SlidePresenter.h>
```

Public Member Functions

unsigned int totalErrors (void)

Returns the sum of the different types of errors that are measured.

Public Attributes

· bool presentationErrorsSuccessfullyChecked

True if presentation errors were successfully checked for. This does not mean that there were no presentation errors, but that there were no presentation error checking errors.

- unsigned int incorrectFrameCounts
- unsigned int lateCopiesToBackBuffer

The number of slides for which the time at which the slide finished being copied to the back buffer was after the actual start time of the slide.

13.39.1 Detailed Description

This struct contains information about errors that were detected during slide presentation. See CX_SlidePresenter:::checkForPresentationErrors().

13.39.2 Member Data Documentation

13.39.2.1 unsigned int CX::CX_SlidePresenter::PresentationErrorInfo::incorrectFrameCounts

The number of slides for which the actual and intended frame counts did not match, indicating that the slide was presented for too many or too few frames.

The documentation for this struct was generated from the following file:

CX_SlidePresenter.h

13.40 CX::Synth::RCFilter Class Reference

#include <CX_ModularSynth.h>

Inherits CX::Synth::ModuleBase.

Public Member Functions

• double getNextSample (void) override

Public Attributes

· ModuleParameter breakpoint

Additional Inherited Members

13.40.1 Detailed Description

This class emulates an analog RC low-pass filter (http://en.wikipedia.org/wiki/Low-pass_filter#-Electronic_low-pass_filters). Setting the breakpoint affects the frequency at which the filter starts to have an effect.

13.40.2 Member Function Documentation

```
13.40.2.1 double CX::Synth::RCFilter::getNextSample(void) [inline], [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following file:

· CX_ModularSynth.h

13.41 CX::Synth::RecursiveFilter Class Reference

```
\verb|#include| < CX\_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Types

enum FilterType { LOW_PASS, HIGH_PASS, BAND_PASS, NOTCH }

Public Member Functions

- void setup (RecursiveFilter::FilterType type)
- double getNextSample (void) override
- void setBreakpoint (double freq)
- void setBandwidth (double bw)

Additional Inherited Members

13.41.1 Detailed Description

This class implements some simple IIR filters. They may not be stable at all frequencies. They are computationally very efficient. They are not highly configurable. They may be chained for sharper frequency response. This class is based on http://www.dspguide.com/ch19.htm.

13.41.2 Member Function Documentation

```
13.41.2.1 double RecursiveFilter::getNextSample (void ) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

13.41.2.2 void RecursiveFilter::setBandwidth (double bw)

Only used for BAND_PASS and NOTCH filters. Sets the width (in frequency domain) of the stop or pass band at which the amplitude is equal to $\sin(PI/4)$ (i.e. .707). So, for example, if you wanted the frequencies 100 Hz above and below the breakpoint to be at .707 of the maximum amplitude, set bw to 100. Of course, past those frequencies the attenuation continues. Larger values result in a less pointy band.

Parameters

bw	The bandwidth.
----	----------------

The documentation for this class was generated from the following files:

- · CX_ModularSynth.h
- CX_ModularSynth.cpp

13.42 CX::CX_SlidePresenter::Slide Struct Reference

```
#include <CX SlidePresenter.h>
```

Public Types

enum {
 NOT_STARTED, COPY_TO_BACK_BUFFER_PENDING, SWAP_PENDING, IN_PROGRESS,
 FINISHED }

Public Attributes

• std::string slideName

The name of the slide. Set by the user during slide creation.

· ofFbo framebuffer

A framebuffer containing image data that will be drawn to the screen during this slide's presentation. If drawingFunction points to a user function, framebuffer will not be drawn.

void(* drawingFunction)(void)

Pointer to a user function that will be called to draw the slide. If this points to a user function, it overrides framebuffer. The drawing function is not required to call ofBackground() or otherwise clear the display before drawing, which allows you to do what is essentially single-buffering using the back buffer as the framebuffer. However, if you want a blank framebuffer, you will have to clear it manually.

· enum

CX::CX_SlidePresenter::Slide:: { ... } slideStatus

SlideTimingInfo intended

The intended timing parameters (i.e. what should have happened if there were no presentation errors).

· SlideTimingInfo actual

The actual timing parameters.

CX Micros copyToBackBufferCompleteTime

The time at which the drawing operations for this slide finished. This is pretty useful to determine if there was an error on the trial (e.g. framebuffer was copied late). If this is greater than actual.startTime, the slide may not have been fully drawn at the time the front and back buffers swapped.

13.42.1 Detailed Description

This struct contains information related to slide presentation using CX SlidePresenter.

13.42.2 Member Enumeration Documentation

13.42.2.1 anonymous enum

Status of the current slide vis a vis presentation.

13.42.3 Member Data Documentation

13.42.3.1 enum { ... } CX::CX_SlidePresenter::Slide::slideStatus

Status of the current slide vis a vis presentation.

The documentation for this struct was generated from the following file:

CX SlidePresenter.h

13.43 CX::CX_SlidePresenter::SlideTimingInfo Struct Reference

```
#include <CX_SlidePresenter.h>
```

Public Attributes

- uint32 t startFrame
- uint32_t frameCount
- CX Micros startTime
- · CX_Micros duration

13.43.1 Detailed Description

Contains information about the presentation timing of the slide.

13.43.2 Member Data Documentation

13.43.2.1 CX_Micros CX::CX_SlidePresenter::SlideTimingInfo::duration

Time amount of time the slide was/should have been presented for.

13.43.2.2 uint32_t CX::CX_SlidePresenter::SlideTimingInfo::frameCount

The number of frames the slide was/should be presented for.

13.43.2.3 uint32_t CX::CX_SlidePresenter::SlideTimingInfo::startFrame

The frame on which the slide started/should have started. Can be compared with the value given by Display.getFrame-Number().

13.43.2.4 CX_Micros CX::CX_SlidePresenter::SlideTimingInfo::startTime

The time at which the slide was/should have been started. Can be compared with values from Clock.getTime().

The documentation for this struct was generated from the following file:

• CX_SlidePresenter.h

13.44 CX::Synth::SoundObjectInput Class Reference

#include <CX_ModularSynth.h>

Inherits CX::Synth::ModuleBase.

Public Member Functions

- void setSoundObject (CX::CX_SoundObject *so, unsigned int channel=0)
- void **setTime** (double t)
- double getNextSample (void) override
- bool canPlay (void)

Additional Inherited Members

13.44.1 Detailed Description

This class allows you to use a CX_SoundObject as the input for the modular synth. It is strictly monophonic, so when you associate a CX_SoundObject with this class, you must pick one channel of the sound to use.

13.44.2 Member Function Documentation

13.44.2.1 bool SoundObjectInput::canPlay (void)

Checks to see if the sound object that is associated with this SoundObjectInput is able to play. It is unable to play if CX SoundObject::isReadyToPlay() is false or if the whole sound has been played.

```
13.44.2.2 double SoundObjectInput::getNextSample(void) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- CX_ModularSynth.h
- CX ModularSynth.cpp

13.45 CX::Synth::SoundObjectOutput Class Reference

```
#include <CX_ModularSynth.h>
Inherits CX::Synth::ModuleBase.
```

Public Member Functions

- void setup (float sampleRate)
- void sampleData (double t)

Public Attributes

CX::CX_SoundObject so

Additional Inherited Members

13.45.1 Detailed Description

This class provides a method of capturing the output of a modular synth and storing it in a CX_SoundObject for later use.

The documentation for this class was generated from the following files:

- · CX_ModularSynth.h
- CX_ModularSynth.cpp

13.46 CX::Synth::Splitter Class Reference

```
#include <CX_ModularSynth.h>
Inherits CX::Synth::ModuleBase.
```

Public Member Functions

• double getNextSample (void) override

Additional Inherited Members

13.46.1 Detailed Description

This class splits a signal and sends that signal to multiple outputs. This can be used for panning effects, for example.

This class is special because it allows multiple outputs.

```
Splitter sp;
Oscillator osc;
Multiplier m1;
Multiplier m2;
StereoStreamOutput out;
osc >> sp;
sp >> m1 >> out.left;
sp >> m2 >> out.right;
```

13.46.2 Member Function Documentation

```
13.46.2.1 double Splitter::getNextSample (void ) [override], [virtual]
```

This function should be overloaded for any derived class that produces values (outputs do not produce values, they produce sound via sound hardware).

Reimplemented from CX::Synth::ModuleBase.

The documentation for this class was generated from the following files:

- · CX ModularSynth.h
- CX_ModularSynth.cpp

13.47 CX::Synth::StereoSoundObjectOutput Class Reference

```
#include <CX_ModularSynth.h>
```

Public Member Functions

- void setup (float sampleRate)
- void sampleData (double t)

Public Attributes

- GenericOutput left
- · GenericOutput right
- CX::CX SoundObject so

13.47.1 Detailed Description

This class provides a method of capturing the output of a modular synth and storing it in a CX_SoundObject for later

This captures stereo audio by taking the output of different streams of data into either the left or right modules that this class has. See the example code.

```
StereoSoundObjectOutput sout;
sout.setup(44100);

Splitter sp;
Oscillator osc;
Multiplier leftM;
Multiplier rightM;

leftM.amount = .1;
rightM.amount = .01;

osc >> sp;
sp >> leftM >> sout.left;
sp >> rightM >> sout.right;

sout.sampleData(2); //Sample 2 seconds worth of data on both channels.
```

The documentation for this class was generated from the following files:

- CX_ModularSynth.h
- CX_ModularSynth.cpp

13.48 CX::Synth::StereoStreamOutput Class Reference

```
#include <CX_ModularSynth.h>
```

Public Member Functions

void setOuputStream (CX::CX SoundStream &stream)

Public Attributes

- · GenericOutput left
- · GenericOutput right

13.48.1 Detailed Description

This class is much like StreamOutput except in stereo.

The documentation for this class was generated from the following files:

- CX_ModularSynth.h
- CX_ModularSynth.cpp

13.49 CX::Synth::StreamOutput Class Reference

```
#include <CX_ModularSynth.h>
```

Inherits CX::Synth::ModuleBase.

Public Member Functions

• void setOuputStream (CX::CX_SoundStream &stream)

14 File Documentation 115

Additional Inherited Members

13.49.1 Detailed Description

This class provides a method of playing the output of a modular synth using a CX SoundStream.

The documentation for this class was generated from the following files:

- CX_ModularSynth.h
- CX ModularSynth.cpp

14 File Documentation

14.1 advancedChangeDetectionTask.cpp File Reference

```
#include "CX_EntryPoint.h"
```

Functions

- int drawStimuli (void)
- int presentStimuli (void)
- int getResponse (void)
- void generateTrials (int trialCount)
- void updateExperiment (void)
- void drawFixation (void)
- void drawBlank (void)
- void drawSampleArray (void)
- void drawTestArray (void)
- ofColor backgroundColor (50)
- void runExperiment (void)

Variables

- CX_TrialController trialController
- CX SlidePresenter SlidePresenter
- CX DataFrame trialDf
- int trialIndex = 0
- int circleRadius = 0

14.1.1 Detailed Description

This example is a more advanced version of the change detection task presented in the basicChangeDetectionTask example. It is not "advanced" because it is more complex, but because it uses more features of CX. It actually ends up being simpler because of how it uses features of CX.

Items that are commented are new, although not all new stuff will neccessarily be commented. The two main features that are demonstrated are CX_DataFrame and CX_TrialController. Using custom units and a custom coordinate system is shown with CX_CoordinateConverter and CX_DegreeToPixelConverter.

14.2 basicChangeDetectionTask.cpp File Reference

```
#include "CX_EntryPoint.h"
```

Functions

- void updateExperiment (void)
- vector< TrialData_t > generateTrials (int trialCount)
- void outputData (void)
- · void drawFixation (void)
- void drawBlank (void)
- void drawSampleArray (const TrialData_t &tr)
- void drawTestArray (const TrialData t &tr)
- ofColor backgroundColor (50)
- void runExperiment (void)

Variables

- CX SlidePresenter SlidePresenter
- vector< TrialData t > trials
- int trialIndex = 0
- int circleRadius = 30
- string trialPhase = "drawStimuli"

14.2.1 Detailed Description

This example shows how to do a simple change-detection experiment using CX. The stimuli are colored circles which are presented in a 3X3 matrix.

Press the S key to indicate that you think the test array is the same or the D key to indicate that you think the test array is different.

14.3 nBack.cpp File Reference

```
#include "CX_EntryPoint.h"
```

Functions

- ofColor backgroundColor (50)
- ofColor textColor (255)
- void **finalSlideFunction** (CX_SlidePresenter::FinalSlideFunctionArgs &info)
- void drawStimulusForTrial (unsigned int trial, bool showInstructions)
- void generateTrials (int numberOfTrials)
- void runExperiment (void)

Variables

- · CX DataFrame df
- CX DataFrame::rowIndex t trialNumber = 0
- int trialCount = 40
- int lastSlideIndex = 0
- int **nBack** = 2
- ofTrueTypeFont letterFont
- ofTrueTypeFont instructionFont
- char targetKey = 'f'
- char nonTargetKey = 'j'
- CX Millis stimulusPresentationDuration = 1000.0
- CX_Millis interStimulusInterval = 1000.0
- CX SlidePresenter SlidePresenter

14.3.1 Detailed Description

This example shows how to implement an N-Back task using an advanced feature of the CX_SlidePresenter (SP). There is a feature of the SP that allows you to give it a pointer to a function that will be called every time the SP has just presented the final slide that it currently has. In your function, you can add more slides to the SP, which will allow it to continue presenting slides. If you don't add any more slides, slide presentation will stop with the currently presented slide.

For this N-Back task, the presentation of stimuli will follow the pattern stimulus-blank-stimulus-blank etc. The idea is that you will load up the SP with the first few stimuli and blanks. The SP will be started and will present the first few stimuli. When it runs out of stimuli, the last slide user function will be called. In this function, we will check for any responses that have been made since the last time the function was called and draw the next stimulus-blank pair. See the definition of finalSlideFunction and setupExperiment for the implementation of these ideas.

Index

AXIS_POSITION_CHANGE	bufferSize	
CX::CX_Joystick::Event, 99	CX::CX_SoundStream::Configuration, 38	
addColumn		
CX::CX_DataFrame, 46	CX::CX_Joystick::Event	
addSilence	AXIS_POSITION_CHANGE, 99	
CX::CX_SoundObject, 81	BUTTON PRESS, 99	
addSound	BUTTON RELEASE, 99	
CX::CX_SoundObject, 81, 82	CX::CX_Keyboard::Event	
advancedChangeDetectionTask.cpp, 115	PRESSED, 100	
api	RELEASED, 100	
CX::CX_SoundStream::Configuration, 38	REPEAT, 100	
appendFunction	CX::CX_Mouse::Event	
CX::Util::CX_TrialController, 95	DRAGGED, 98	
appendRow	MOVED, 98	
CX::CX_DataFrame, 46	PRESSED, 98	
appendSlide	RELEASED, 98	
CX::CX_SlidePresenter, 77	SCROLLED, 98	
appendSlideFunction	CX::CX SlidePresenter	
CX::CX_SlidePresenter, 77	FIX_TIMING_FROM_FIRST_SLIDE, 77	
applyGain	PROPAGATE DELAYS, 77	
CX::CX_SoundObject, 82	CX, 21	
arrayToVector	CX::Algo, 22	
CX::Util, 28	fullyCross, 22	
at	generateSeparatedValues, 23	
CX::CX_DataFrame, 46	CX::CX_Clock, 39	
availableEvents	getDateTimeString, 40	
CX::CX_Joystick, 63	getExperimentStartDateTimeString, 41	
CX::CX_Keyboard, 64	getExperimentStartTime, 41	
CX::CX Mouse, 69	getSystemTime, 41	
_ ,	getTime, 41	
BUTTON PRESS	precisionTest, 41	
CX::CX_Joystick::Event, 99	CX::CX_DataFrame, 44	
BUTTON RELEASE	addColumn, 46	
CX::CX_Joystick::Event, 99	appendRow, 46	
BLOCKING estimateFramePeriod	at, 46	
CX::CX_Display, 58	clear, 46	
BLOCKING setAutoSwapping	columnNames, 46	
CX::CX_Display, 58	copyColumn, 47	
BLOCKING_setSound	copyColumns, 47	
CX::CX_SoundObjectPlayer, 87	copyRows, 47	
BLOCKING_swapFrontAndBackBuffers	deleteColumn, 47	
CX::CX Display, 58	deleteRow, 48	
BLOCKING_waitForOpenGL	operator(), 48	
CX::CX_Display, 58	operator=, 48	
basicChangeDetectionTask.cpp, 116	print, 48, 49	
beginDrawingNextSlide	printToFile, 49	
CX::CX_SlidePresenter, 78	readFromFile, 50	
beginDrawingToBackBuffer	reorderRows, 50	
CX::CX_Display, 58	setRowCount, 50	
binomialDeviates	shuffleRows, 51	
CX::CX_RandomNumberGenerator, 71	CX::CX_DataFrameCell, 51	

CX_DataFrameCell, 52	captureOFLogMessages, 66
copyCellTo, 53	error, 66
getStoredType, 54	fatalError, 66
operator=, 54	flush, 66
store, 54	level, 66
storeVector, 54	levelForAllModules, 67
to, 54	levelForConsole, 67
toVector, 55	levelForFile, 67
CX::CX_DataFrameColumn, 55	log, 67
CX::CX_DataFrameRow, 55	notice, 67
CX::CX_Display, 57	setMessageFlushCallback, 67
BLOCKING_estimateFramePeriod, 58	timestamps, 68
BLOCKING_setAutoSwapping, 58	verbose, 68
BLOCKING_swapFrontAndBackBuffers, 58	warning, 68
BLOCKING_waitForOpenGL, 58	CX::CX_Mouse, 68
beginDrawingToBackBuffer, 58	availableEvents, 69
drawFboToBackBuffer, 59	clearEvents, 69
endDrawingToBackBuffer, 59	getCursorPosition, 69
estimateNextSwapTime, 59	getNextEvent, 69
getCenterOfDisplay, 59	setCursorPosition, 69
getFrameNumber, 59	showCursor, 69
getFramePeriod, 59	CX::CX_Mouse::Event, 97
getLastSwapTime, 59	MouseEventType, 98
getResolution, 60	CX::CX_RandomNumberGenerator, 69
hasSwappedSinceLastCheck, 60	binomialDeviates, 71
isAutomaticallySwapping, 60	CX_RandomNumberGenerator, 70
setFullScreen, 60	getMaximumRandomInt, 71
setWindowResolution, 60	getMinimumRandomInt, 71
setWindowTitle, 60	getSeed, 71
setup, 60	normalDeviates, 71
swapFrontAndBackBuffers, 61	randomExclusive, 72
CX::CX_InputManager, 61	randomInt, 72
pollEvents, 61	sample, 73
setup, 62	setSeed, 74
CX::CX_Joystick, 62	shuffleVector, 74
availableEvents, 63	uniformDeviate, 74
clearEvents, 63	uniformDeviates, 74
getAxisPositions, 63	CX::CX_SlidePresenter, 75
getButtonStates, 63	appendSlide, 77
getJoystickName, 63	appendSlideFunction, 77
getNextEvent, 63	beginDrawingNextSlide, 78
pollEvents, 63	checkForPresentationErrors, 78
setup, 63	clearSlides, 78
CX::CX_Joystick::Event, 98	endDrawingCurrentSlide, 78
JoystickEventType, 99	ErrorMode, 77
CX::CX_Keyboard, 63	getActualFrameCounts, 78
availableEvents, 64	getActualPresentationDurations, 79
clearEvents, 64	getSlides, 79
getNextEvent, 64	setup, 79
isKeyPressed, 64	startSlidePresentation, 80
CX::CX_Keyboard::Event, 99	update, 80
key, 100	CX::CX_SlidePresenter::Configuration, 38
KeyboardEventType, 100	CX::CX_SlidePresenter::FinalSlideFunctionArgs, 100
CX::CX_Logger, 66	CX::CX_SlidePresenter::PresentationErrorInfo, 107
_	

incorrectFrameCounts, 107	getDeviceList, 93
CX::CX_SlidePresenter::Slide, 109	getLastSwapTime, 93
slideStatus, 110	getRtAudioInstance, 93
CX::CX_SlidePresenter::SlideTimingInfo, 110	getSampleFrameNumber, 93
duration, 111	getStreamLatency, 93
frameCount, 111	hasSwappedSinceLastCheck, 93
startFrame, 111	listDevices, 94
startTime, 111	setup, 94
CX::CX_SoundObject, 80	start, 94
addSilence, 81	stop, 94
	CX::CX SoundStream::Configuration, 37
addSound, 81, 82	_
applyGain, 82	api, 38
clear, 82	bufferSize, 38
deleteAmount, 82	sampleRate, 38
getLength, 82	streamOptions, 38
getNegativePeak, 83	CX::CX_SoundStream::InputEventArgs, 102
getPositivePeak, 83	CX::CX_SoundStream::OutputEventArgs, 106
getRawDataReference, 83	CX::Draw, 24
getSampleFrameCount, 83	centeredString, 24
getTotalSampleCount, 83	squircleToPath, 24
isLoadedSuccessfully, 83	star, 24
isReadyToPlay, 83	starToPath, 26
loadFile, 83	CX::Instances, 26
multiplyAmplitudeBy, 85	CX::Private, 26
multiplySpeed, 85	CX::Synth, 27
normalize, 85	CX::Synth::Adder, 32
resample, 85	getNextSample, 33
reverse, 85	CX::Synth::AdditiveSynth, 33
setChannelCount, 85	getNextSample, 34
setFromVector, 86	pruneLowAmplitudeHarmonics, 34
setLength, 86	setAmplitudes, 34
stripLeadingSilence, 86	setHarmonicSeries, 36
•	setStandardHarmonicSeries, 36
writeToFile, 86	
CX::CX_SoundObjectPlayer, 87	CX::Synth::Clamper, 36
BLOCKING_setSound, 87	getNextSample, 37
play, 88	CX::Synth::Envelope, 97
setTime, 88	getNextSample, 97
setup, 88	CX::Synth::FIRFilter, 101
startPlayingAt, 88	getNextSample, 101
stop, 88	CX::Synth::Mixer, 102
CX::CX_SoundObjectRecorder, 89	getNextSample, 103
getSoundObject, 90	CX::Synth::ModuleBase, 103
setSoundObject, 90	getNextSample, 104
setup, 90	operator>>, 104
startRecording, 90	setData, 104
stopRecording, 90	CX::Synth::Multiplier, 104
CX::CX_SoundStream, 90	getNextSample, 105
closeStream, 92	setGain, 105
convertApiToString, 92	CX::Synth::Oscillator, 105
convertApisToString, 92	getNextSample, 106
convertApisToStrings, 92	CX::Synth::RCFilter, 107
estimateNextSwapTime, 92	getNextSample, 108
•	· · · · · · · · · · · · · · · · · · ·
getCompiledApis, 92	CX::Synth::RecursiveFilter, 108
getConfiguration, 93	getNextSample, 109

setBandwidth, 109	canPlay
CX::Synth::SoundObjectInput, 111	CX::Synth::SoundObjectInput, 11
canPlay, 111	captureOFLogMessages
getNextSample, 111	CX::CX_Logger, 66
CX::Synth::SoundObjectOutput, 112	centeredString
CX::Synth::Splitter, 112	CX::Draw, 24
getNextSample, 113	checkForPresentationErrors
CX::Synth::StereoSoundObjectOutput, 113	CX::CX_SlidePresenter, 78
CX::Synth::StereoStreamOutput, 114	checkOFVersion
CX::Synth::StreamOutput, 114	CX::Util, 29
CX::Util, 28	clamp
arrayToVector, 28	CX::Util, 29
checkOFVersion, 29	clear
clamp, 29	CX::CX_DataFrame, 46
degreesToPixels, 29	CX::CX_SoundObject, 82
intVector, 29	clearEvents
pixelsToDegrees, 30	CX::CX_Joystick, 63
repeat, 30	CX::CX_Keyboard, 64
round, 30	CX::CX Mouse, 69
sequence, 31	clearSlides
sequence, 31 sequenceAlong, 31	CX::CX_SlidePresenter, 78
	Clock
sequenceSteps, 31	
vectorToString, 32	Timing, 18
writeToFile, 32	closeStream
CX::Util::CX_CoordinateConverter, 41	CX::CX_SoundStream, 92
CX_CoordinateConverter, 42	columnNames
operator(), 42, 43	CX::CX_DataFrame, 46
setAxisInversion, 43	convertApiToString
setMultiplier, 43	CX::CX_SoundStream, 92
setOrigin, 43	convertApisToString
setUnitConverter, 43	CX::CX_SoundStream, 92
CX::Util::CX_DegreeToPixelConverter, 56	convertApisToStrings
CX_DegreeToPixelConverter, 56	CX::CX_SoundStream, 92
operator(), 57	copyCellTo
CX::Util::CX_LengthToPixelConverter, 65	CX::CX_DataFrameCell, 53
CX_LengthToPixelConverter, 65	copyColumn
operator(), 65	CX::CX_DataFrame, 47
CX::Util::CX_TrialController, 95	copyColumns
appendFunction, 95	CX::CX_DataFrame, 47
reset, 96	copyRows
setCurrentFunction, 96	CX::CX_DataFrame, 47
update, 96	onon_batal famo, in
CX_CoordinateConverter	DRAGGED
CX::Util::CX_CoordinateConverter, 42	CX::CX_Mouse::Event, 98
CX_DataFrameCell 52	Data, 12 degreesToPixels
CX::CX_DataFrameCell, 52	•
CX_DegreeToPixelConverter	CX::Util, 29
CX::Util::CX_DegreeToPixelConverter, 56	deleteAmount
CX_LengthToPixelConverter	CX::CX_SoundObject, 82
CX::Util::CX_LengthToPixelConverter, 65	deleteColumn
CX_LogLevel	CX::CX_DataFrame, 47
Error Logging, 14	deleteRow
CX_RandomNumberGenerator	CX::CX_DataFrame, 48
CX::CX_RandomNumberGenerator, 70	Display

Entry Point, 13	getDateTimeString
drawFboToBackBuffer	CX::CX_Clock, 40
CX::CX_Display, 59	getDeviceList
duration	CX::CX_SoundStream, 93
CX::CX_SlidePresenter::SlideTimingInfo, 111	getExperimentStartDateTimeString
	CX::CX_Clock, 41
endDrawingCurrentSlide	getExperimentStartTime
CX::CX_SlidePresenter, 78	CX::CX_Clock, 41
endDrawingToBackBuffer	getFrameNumber
CX::CX_Display, 59	CX::CX_Display, 59
Entry Point, 13	getFramePeriod
Display, 13	CX::CX_Display, 59
Input, 13	getJoystickName
Log, 13	CX::CX_Joystick, 63
RNG, 13	getLastSwapTime
runExperiment, 13	CX::CX_Display, 59
error	CX::CX_SoundStream, 93
CX::CX_Logger, 66	
Error Logging, 14	getLength
CX_LogLevel, 14	CX::CX_SoundObject, 82
ErrorMode	getMaximumRandomInt
CX::CX_SlidePresenter, 77	CX::CX_RandomNumberGenerator, 7
estimateNextSwapTime	getMinimumRandomInt
CX::CX_Display, 59	CX::CX_RandomNumberGenerator, 7
CX::CX_SoundStream, 92	getNegativePeak
om.or_ooundotroum, oz	CX::CX_SoundObject, 83
FIX_TIMING_FROM_FIRST_SLIDE	getNextEvent
CX::CX_SlidePresenter, 77	CX::CX_Joystick, 63
fatalError	CX::CX_Keyboard, 64
CX::CX_Logger, 66	CX::CX_Mouse, 69
flush	getNextSample
CX::CX_Logger, 66	CX::Synth::Adder, 33
frameCount	CX::Synth::AdditiveSynth, 34
CX::CX_SlidePresenter::SlideTimingInfo, 111	CX::Synth::Clamper, 37
fullyCross	CX::Synth::Envelope, 97
CX::Algo, 22	CX::Synth::FIRFilter, 101
OX 11g0, 22	CX::Synth::Mixer, 103
generateSeparatedValues	CX::Synth::ModuleBase, 104
CX::Algo, 23	CX::Synth::Multiplier, 105
getActualFrameCounts	CX::Synth::Oscillator, 106
CX::CX SlidePresenter, 78	CX::Synth::RCFilter, 108
getActualPresentationDurations	CX::Synth::RecursiveFilter, 109
CX::CX_SlidePresenter, 79	CX::Synth::SoundObjectInput, 111
getAxisPositions	CX::Synth::Splitter, 113
CX::CX_Joystick, 63	getPositivePeak
getButtonStates	CX::CX SoundObject, 83
CX::CX_Joystick, 63	getRawDataReference
getCenterOfDisplay	CX::CX_SoundObject, 83
CX::CX Display, 59	getResolution
— · ·	-
getCompiledApis	CX::CX_Display, 60
CX::CX_SoundStream, 92	getRtAudioInstance
getConfiguration	CX::CX_SoundStream, 93
CX::CX_SoundStream, 93	getSampleFrameCount
getCursorPosition	CX::CX_SoundObject, 83
CX::CX_Mouse, 69	getSampleFrameNumber

CX::CX_SoundStream, 93	CX::CX_SoundStream, 94
getSeed	loadFile
CX::CX_RandomNumberGenerator, 71	CX::CX_SoundObject, 83
getSlides	Log
CX::CX_SlidePresenter, 79	Entry Point, 13
getSoundObject	log
CX::CX_SoundObjectRecorder, 90	CX::CX_Logger, 67
getStoredType	
CX::CX_DataFrameCell, 54	MOVED
getStreamLatency	CX::CX_Mouse::Event, 98
CX::CX_SoundStream, 93	MouseEventType
getSystemTime	CX::CX_Mouse::Event, 98
CX::CX_Clock, 41	multiplyAmplitudeBy
getTime	CX::CX_SoundObject, 85
CX::CX_Clock, 41	multiplySpeed
getTotalSampleCount	CX::CX_SoundObject, 85
CX::CX SoundObject, 83	
_ , ,	nBack.cpp, 116
hasSwappedSinceLastCheck	normalDeviates
CX::CX_Display, 60	CX::CX_RandomNumberGenerator, 71
CX::CX_SoundStream, 93	normalize
	CX::CX_SoundObject, 85
incorrectFrameCounts	notice
CX::CX_SlidePresenter::PresentationErrorInfo, 107	CX::CX_Logger, 67
Input	
Entry Point, 13	operator>>
Input Devices, 15	CX::Synth::ModuleBase, 104
intVector	operator()
CX::Util, 29	CX::CX_DataFrame, 48
isAutomaticallySwapping	CX::Util::CX_CoordinateConverter, 42, 43
CX::CX_Display, 60	CX::Util::CX_DegreeToPixelConverter, 57
isKeyPressed	CX::Util::CX_LengthToPixelConverter, 65
CX::CX_Keyboard, 64	operator=
isLoadedSuccessfully	CX::CX_DataFrame, 48
CX::CX_SoundObject, 83	CX::CX_DataFrameCell, 54
isReadyToPlay	
CX::CX_SoundObject, 83	PRESSED
	CX::CX_Keyboard::Event, 100
JoystickEventType	CX::CX_Mouse::Event, 98
CX::CX_Joystick::Event, 99	PROPAGATE_DELAYS
	CX::CX_SlidePresenter, 77
key	pixelsToDegrees
CX::CX_Keyboard::Event, 100	CX::Util, 30
KeyboardEventType	play
CX::CX_Keyboard::Event, 100	CX::CX_SoundObjectPlayer, 88
	pollEvents
level	CX::CX_InputManager, 61
CX::CX_Logger, 66	CX::CX_Joystick, 63
levelForAllModules	precisionTest
CX::CX_Logger, 67	CX::CX_Clock, 41
levelForConsole	print
CX::CX_Logger, 67	CX::CX_DataFrame, 48, 49
levelForFile	printToFile
CX::CX_Logger, 67	CX::CX_DataFrame, 49
listDevices	pruneLowAmplitudeHarmonics

CX::Synth::AdditiveSynth, 34	setData
RELEASED	CX::Synth::ModuleBase, 104
CX::CX_Keyboard::Event, 100	setFromVector
	CX::CX_SoundObject, 86
CX::CX_Mouse::Event, 98	setFullScreen
REPEAT	CX::CX_Display, 60
CX::CX_Keyboard::Event, 100	setGain
RNG	CX::Synth::Multiplier, 105
Entry Point, 13	setHarmonicSeries
randomExclusive	CX::Synth::AdditiveSynth, 36
CX::CX_RandomNumberGenerator, 72	setLength
randomInt	CX::CX SoundObject, 86
CX::CX_RandomNumberGenerator, 72	setMessageFlushCallback
Randomization, 16	CX::CX_Logger, 67
readFromFile	setMultiplier
CX::CX_DataFrame, 50	CX::Util::CX_CoordinateConverter, 43
reorderRows	setOrigin
CX::CX_DataFrame, 50	CX::Util::CX_CoordinateConverter, 43
repeat	setRowCount
CX::Util, 30	
resample	CX::CX_DataFrame, 50
CX::CX SoundObject, 85	setSeed
reset	CX::CX_RandomNumberGenerator, 74
CX::Util::CX TrialController, 96	setSoundObject
reverse	CX::CX_SoundObjectRecorder, 90
CX::CX_SoundObject, 85	setStandardHarmonicSeries
round	CX::Synth::AdditiveSynth, 36
CX::Util, 30	setTime
runExperiment	CX::CX_SoundObjectPlayer, 88
Entry Point, 13	setUnitConverter
Entry Point, 13	CX::Util::CX_CoordinateConverter, 43
SCROLLED	setWindowResolution
CX::CX_Mouse::Event, 98	CX::CX_Display, 60
sample	setWindowTitle
CX::CX_RandomNumberGenerator, 73	CX::CX Display, 60
	setup
sampleRate	CX::CX_Display, 60
CX::CX_SoundStream::Configuration, 38	CX::CX_InputManager, 62
sequence	CX::CX Joystick, 63
CX::Util, 31	- • ·
sequenceAlong	CX::CX_SlidePresenter, 79
CX::Util, 31	CX::CX_SoundObjectPlayer, 88
sequenceSteps	CX::CX_SoundObjectRecorder, 90
CX::Util, 31	CX::CX_SoundStream, 94
setAmplitudes	showCursor
CX::Synth::AdditiveSynth, 34	CX::CX_Mouse, 69
setAxisInversion	shuffleRows
CX::Util::CX_CoordinateConverter, 43	CX::CX_DataFrame, 51
setBandwidth	shuffleVector
CX::Synth::RecursiveFilter, 109	CX::CX_RandomNumberGenerator, 74
setChannelCount	slideStatus
CX::CX_SoundObject, 85	CX::CX_SlidePresenter::Slide, 110
setCurrentFunction	Sound, 17
CX::Util::CX_TrialController, 96	squircleToPath
setCursorPosition	CX::Draw, 24
CX::CX Mouse, 69	star
37111371 1110400, 00	Ola.

```
CX::Draw, 24
                                                        warning
starToPath
                                                            CX::CX Logger, 68
                                                        writeToFile
    CX::Draw, 26
start
                                                            CX::CX SoundObject, 86
                                                            CX::Util, 32
    CX::CX_SoundStream, 94
startFrame
    CX::CX SlidePresenter::SlideTimingInfo, 111
startPlayingAt
    CX::CX SoundObjectPlayer, 88
startRecording
    CX::CX_SoundObjectRecorder, 90
startSlidePresentation
    CX::CX_SlidePresenter, 80
startTime
    CX::CX_SlidePresenter::SlideTimingInfo, 111
stop
    CX::CX SoundObjectPlayer, 88
    CX::CX_SoundStream, 94
stopRecording
    CX::CX_SoundObjectRecorder, 90
store
    CX::CX_DataFrameCell, 54
storeVector
    CX::CX DataFrameCell, 54
streamOptions
    CX::CX_SoundStream::Configuration, 38
stripLeadingSilence
    CX::CX SoundObject, 86
swapFrontAndBackBuffers
    CX::CX_Display, 61
timestamps
    CX::CX_Logger, 68
Timing, 18
    Clock, 18
    CX::CX_DataFrameCell, 54
toVector
    CX::CX_DataFrameCell, 55
uniformDeviate
    CX::CX_RandomNumberGenerator, 74
uniformDeviates
    CX::CX_RandomNumberGenerator, 74
update
    CX::CX_SlidePresenter, 80
    CX::Util::CX TrialController, 96
Utility, 19
vectorToString
    CX::Util, 32
verbose
    CX::CX_Logger, 68
Video, 20
```