https://github.com/davidnbresch/climada module country risk david.bresch@gmail.com melanie.bieli@bluewin.ch

This module runs all (available) perils for one country¹. It generates earthquake (EQ), tropical cyclone (TC), torrential rain (TR) and storm surge (TS) hazard event sets, checks for European winter storm (WS) exposure and runs all risk calculations for a given country (see option for any state/province or admin1 further below).

Also, the module calculates the economic loss (i.e. the full range of economic costs in the wake of a natural disaster) associated with the hazard event sets².

```
country risk=country risk calc(country name)
cr_entity_value_GDP_adjust(entity_file_regexp)
cr economic loss calc(country risk) (calls cr get damage weight)
country risk report(country risk)
cr loss multiplier plot(country names)
and (see further below)
country admin1 risk calc(country name, province_name)
climada nightlight entity(country name,province name)
Procedure is as follows:
1) generate centroids for the country (uses climada create GDP entity<sup>3</sup>)
2) figure which hazards affect the country
3) create the hazard event sets, using
      - climada to hazard set (tropical cyclone wind<sup>4</sup>)
      - climada tr hazard set (tropical cyclone rain<sup>5</sup>)
```

- climada ts hazard set (tropical cyclone surge⁶)
- eq global hazard set (earthquake⁷)
- European winter storm (hazard not generated, just assigned⁸)
- 4) run the risk calculation for all hazards
- 5) run the economic loss calculation for all hazards

In essence, you define the country and the code runs the generation of centroids, default assets (from nightlight intensity, see climada module GDP_entity) and the EQ, TC, TR and TS hazard event sets plus checks for WS Europe exposure. It even figures whether the country is exposed

¹ See further below for country admin1 risk_calc, which runs the calculation for one state/province in a given country. The routine climada country risk also allows for processing a list or even all countries. As always, use help climada country risk to get a detailed description on the options.

See appendix for details on the calculation of economic loss based on the damages in the hazard event set.

³ See https://github.com/davidnbresch/climada_module_GDP_entity and further below for

climada nightlight entity which allows to generate a high-resolution entity for any country and state/province. Core climada contains the basic tropical cyclone hazard, but please add the module

https://github.com/davidnbresch/climada_module_tc_hazard_advanced to generate useful probabilistic hazard event sets (see parameter probabilistic in country_risk_calc). Please consider to run

climada to get unisys databases (climada core) in order to download the latest tropical cyclone databases for all ocean basins (core climate comes with TC Atlantic to start with).

See climada module https://github.com/davidnbresch/climada module tc rain

⁶ See climada module https://github.com/davidnbresch/climada_module_tc_surge_which also requires the module https://github.com/davidnbresch/climada module etopo

See climada module https://github.com/davidnbresch/climada module eq global

⁸ See climada module for European winter storm, which contains the hazard sets https://github.com/davidnbresch/climada module ws europe

to more than one ocean basin and in such a case generates a suite of TC/TS/TR hazard event sets for each ocean basin. The code is ready for upgrade with additional hazards (usually a new hazard is a new climada module). That's why the code notifies the user if the specific hazard module is missing (even indicates the github location where to get it from).

Simply call e.g. country_risk_calc('El Salvador')

If called without any argument, a list dialog to select the country pops up. See code header for details, i.e. help country risk calc

Behind the scenes, the code centroids_generate_hazard_sets does the heavy lifting, i.e. steps 2) and 3) from above. This way one can generate all relevant hazard sets with one call to centroids_generate_hazard_sets for any set of centroids (e.g. only a part of a country, a region, a city...⁹):

```
centroids_hazard_info=...
  centroids generate hazard sets(centroids, force recalc, check plots)
```

The resulting structure centroids_hazard_info contains the names of the generated hazard sets (or the ones generated earlier if just called to check for step 2) in centroids_hazard_info.res.hazard(i).hazard_set_file (the somewhat complicated nested structure is due to the flexibility required by country_risk_calc).




Figure: Step 1 (generate centroids, assets distribution, color scale indicates value per centroid) and step 2 (hazard selection). The green box shows the selection area around the country, the blue dots are all the TC track nodes (historic) and the red dots the epicenters (historic). This figure is generated if check_plot=1 in the call, e.g. country_risk_calc('El Salvador',0,0,1).

2

⁹ See e.g. the code climada_cut_out_GDP_entity from https://github.com/davidnbresch/climada_module_GDP_entity and also country_admin1_risk_calc and climada nightlight entity further below (part of module country risk)




Figure: The most intense single event for all hazard generated for El Salvador (Step 3). Note that El Salvador is both exposed to tropical cyclones from the East and West, that's why there are two hazard events sets for TC/TS/TR, one for the Atlantic side (atl for Atlantic), one for the Pacific side (epa for East Pacific Ocean). The earthquake model is global. Note further the nice feature of hazard (or peril) – dependent color scales; and the coarser resolution of centroids (blue) around the country (with red dots at high-density centroids) to support plotting hazard intensities around the country, too. This figure is generated if check_plot=1 in the call, e.g. country risk calc('El Salvador',0,0,1)




Figure: The resulting damage frequency curves (DFC) for all seven (!) hazards affecting El Salvador (values just for illustration, based on dummy damage functions). This figure is generated with check_plot=1 in the call, e.g.

country_risk_report(country_risk_calc('El Salvador',1,1),0,1)

cr_entity_value_GDP_adjust: Scale up asset values based on a country's estimated total asset value. In this step, the entities' asset values are first normalized and then multiplied by a factor that depends on a country's income group (low, lower middle, upper middle, or high). The choice of this factor is based on a comparison of Climada entities to estimates for total asset values in countries where such data are available. This comparison showed that in general, adjusting the Climada asset values requires a higher multiplication factor the wealthier a country is. Thus, as a rule of thumb, the value of all assets in a country can be estimated by

where GDP is the country's gross domestic product, and income_group_factor ranges from 2 for low income countries to 5 for high income countries.

cr_economic_loss_calc: Major natural disasters can and do have severe negative short-run economic impacts, the severity of which depends on the affected country's resilience, or ability to recover. cr_economic_loss_calc calculates the economic damages resulting from the simple property damages in the hazard event set, taking into account socio-economic data on the country's financial strength, supply chain risk profile, resilience and preparedness for natural disasters (see appendix for details).

```
country_risk_report: Comes in handy if one runs some select countries, e.g:
country_risk=country_risk_calc('Barbados')
country_risk(2)=country_risk_calc('El Salvador')
country_risk(3)=country_risk_calc('Costa Rica')
```

And then country_risk_report(country_risk,0) results in the following output (to stdout, also an Excel or .csv file is written¹⁰):

```
Barbados (1)
  TR EL=36572051.496470
                               (8.481508%o)
                                                       Barbados TR atl
  TC EL=23083330.494007
                               (5.353308%o)
                                                       Barbados_TC_atl
  TS EL=7531.966739
                                (0.001747%0)
                                                       Barbados_TS_atl
  EQ EL=0.000000
                               (0.000000%o)
                                                       Barbados EQ global
ElSalvador (2)
  EO EL=415631535.361110
                               (17.943889%o)
                                                       ElSalvador_EQ_global
  TR EL=141613002.072040
                                                       ElSalvador TR epa
                               (6.113800%o)
  TC EL=59386249.565168
                                                       ElSalvador TC atl
                               (2.563858%o)
  TC EL=16152772.894979
                               (0.697357\%0)
                                                       ElSalvador_TC_epa
                                                       ElSalvador_TR_atl
ElSalvador_TS epa
  TR EL=621784.438763
                               (0.026844%0)
  TS EL=0.000000
                               (0.000000%0)
  TS EL=0.000000
                               (0.000000%o)
                                                       ElSalvador_TS_atl
Costa Rica (3)
  EQ EL=523833928.441207
                               (12.396559%0)
                                                       Costa Rica EQ global
  TR EL=1530537.767294
                               (0.036220%o)
                                                       Costa Rica_TR_epa
  TC EL=73978.520263
                               (0.001751\%0)
                                                       Costa Rica TC epa
                               (0.000136%o)
                                                       Costa Rica_TR_atl
  TR EL=5765.009179
  TS EL=1689.347413
                               (0.000040%o)
                                                       Costa Rica_TS_atl
  TC EL=60.830655
                                (0.00001\%0)
                                                       Costa Rica TC atl
  TS EL=0.000000
                                                       Costa Rica_TS_epa
                                (0.000000%0)
```




Figure: The local damage for a given peril (here EQ) for one country (here Costa Rica) in spatial resolution (e.g. at each centroid). Produced by the call (following from above resulting structure country risk):

```
country_i=3; hazard_i=7<sup>11</sup>;
climada_circle_plot(...
country_risk(country_i).res.hazard(hazard_i).EDS.ED_at_centroid,...
country_risk(country_i).res.hazard(hazard_i).EDS.assets.Longitude,...
country_risk(country_i).res.hazard(hazard_i).EDS.assets.Latitude)
```

 ¹⁰ The report does contain the annual expected damage (ED) as well as defined return periods (such as 100 and 250 years). In case writing an Excel file fails, a .csv file is written.
 11 Note that the number seven here corresponds to the 7th hazard analyzed (EQ). The report to stdout shows EQ as

[&]quot;Note that the number seven here corresponds to the 7th hazard analyzed (EQ). The report to stdout shows EQ as the first result, since country_risk_report sorts by descending damage, unless it is called with the second parameter (print unsorted) set to 1.

country admin1 risk calc: Same as country risk calc, but for a state or province (admin1 level) of any given country. Run the all (available) perils for one country's admin1 level. Obtain the admin1 boundaries (from www.naturalearthdata.com, shape files already part of the data that comes with the country risk module) and carve out the respective centroids (set Value at all others to zero). Run the risk calculation for each admin1 for all hazards. In case one would like to skip hazards, just (temporarily) remove the respective {country_name}_*.mat hazard event sets. ONLY makes sense if country risk calc has been run for the respective country (we keep it like this, as automatic mode might trigger lots of un-wanted calculations). If not, the code terminates with the respective messages (no entity found, no hazard set(s) found...). But one can run country admin1 risk calc for more than one country, if the respective countries have been run as country risk calc. NOTE: Before using this code, make yourself familiar with country risk calc and country risk report (same format as country risk calc).

climada nightlight entity: Construct an entity file based on high-res (1km!) night light data¹². Reads an image file with nightlight density¹³ and matches it to the local geography. Prompts for country (admin0) and state/province (admin1), constrains the active centroids (with values>0) to the selected country or admin1 and saves the entity. Since we're dealing with admin1, no automatic scaling or allocation of GDP to centroids is performed (for this, see climada create GDP entity¹⁴).




Figure: Brazil value distribution on 1km (!) resolution (left, zoomed in right) as generated by climada nightlight entity('Brazil','',2)

¹² One can also run it at moderate (10x10km) resolution, see parameter selections, i.e. type help

6

climada_highres_entity

The climada module country_risk comes with the .mat file F182012.v4c_web.stable_lights.avg_vis.mat (24MB), since the .tif image is about 700MB. See http://ngdc.noaa.gov/eog/dmsp/downloadV4composites.html#AVSLCFC3 to obtain the file http://ngdc.noaa.gov/eog/data/web_data/v4composites/F182012.v4.tar and unzip the file F182012.v4c web.stable lights.avg vis.tif in there to the /data folder of country risk module. As the .tif is so much larger, the climada module country risk comes with the .mat file, but does not contain the original (.tif). Should the .mat file not exist, climada nightlight entity creates it on first call. Please note that the GDP entity could also deal with such a high-res dataset (see respective documentation). ¹⁴ See footnote 8 above

Appendix

A. Calculation of economic damage in cr_economic_loss_calc

Starting point for the economic loss calculation is damage(event_i), i.e. the property damage calculated by climada_EDS_calc. The economic loss then also includes secondary losses to an economy including e.g. lost ouput, retail sales, wages, costs to business form rerouting goods and services around the affected area, reduced taxable receipts, etc.

The underlying rationale of the calculation is that a property damage resulting from a natural disaster does not have a major impact on a country's economy as long as the damage is small compared to the country's GDP, and as long as adequate financing and national resources exist. However, if a damage is big, it will be exacerbated depending on how well a country is "in shape" to deal with major shocks.

cr_economic_loss_calc intends to estimate the economic damage as it manifests itself about 3-6 months after a disaster occurred. This first-round effect of natural disasters is usually that income and output (GDP) fall. What happens in the next round then depends on the way the country or region responds to the crisis. For example, Japan is a strong economy and has the resources to start rebuilding quickly, while smaller and badly managed countries such as Haiti can suffer severe long-term effects. It should be noted that cr_economic_loss_calc only calculates the temporary dip following the first months after a disaster (see Figure). After that initial dip, different scenarios can lead to no, positive or negative follow-on effects over the long run. In particular, a natural disaster can even positively affect total factor productivity, e.g. when it leads to the replacement of damaged, outdated production facilities and physical infrastructure with state-of-the-art facilities and infrastructure. However, as noted above, cr_economic_loss_calc only deals with the calculation of the initial impact, not with the long-term scenarios.




Figure: Possible trajectories of GDP after a disaster¹⁵. The delta is the initial temporary dip cr_economic_loss_calc provides an estimate for.

7

¹⁵ Source: Hochrainer, 2006 https://openknowledge.worldbank.org/bitstream/handle/10986/4162/WPS4968.pdf?sequence=1

In cr_economic_loss_calc, the economic loss caused by the natural disaster is calculated according to:

```
economic_loss(event_i) = damage(event_i) * loss_multiplier
```

where loss_multiplier is defined by:

```
loss multiplier =
```

```
1 + cr get damage weight(damage(event i)/GDP) * country damage factor
```

with

 $\verb|cr_get_damage_weight|: function that determines how much weight a damage should be given based on its ratio to GDP|$

Hence, country_damage factor consists of four terms:

 financial_strength measures a country's economic health and ability to finance the recovery.

 BI_and_supply_chain_risk measures a country's risk of disaster-related business and supply chain interruption

```
BI_and_supply_chain_risk = GDP_industry ... + FM resilience index supply chain/100
```

• natural_hazard_economic_exposure assesses which countries have a concentration of their total economic output exposed to natural hazards natural hazard economic exposure = ...

```
1 - Natural_Hazards_Economic_Exposure/10
```

 disaster_resilience measures the quality of a country's natural hazard risk management, i.e., the country's "preparedness" to deal with the consequences of a disaster

See economic_indicators_mastertable.xls (in the data folder of the country_risk module¹⁶) for more information on the four components of country_damage_factor (and their respective subcomponents).

¹⁶ Download: https://github.com/davidnbresch/climada_module_country_risk