

MSFS FlightBag V 0.67.0.67

See (V0.67) indications for updates from the previous version (V0.65)

Flight bag providing ...

- Standalone or Part of the MSFS HudBar Windows
- Shelf for image documents either JPG, PNG or GIF images or **PDF documents** for reference (added V0.67)
- Airport centric Map display
- METAR retrieval
- Profile Calculator
- Performance and Touchdown data
- Notepad
- Route and document integration with SimBrief and MSFS Route and Flightplan files
- Airport Reports (new V0.67)

MSFS_FlightBag is a standalone application but also integrated in the **MSFS_HudBar** application.

Both are the same and share the same settings, data and configuration.

The integrated version attempts to gather the flight plan departure and arrival airports where the standalone version expects those to be entered in the Config. Tab – otherwise they are the same.



IMPORTANT:

MSFS_FlightBag makes extensive use of airport, runway and navigation data intended for the simulator.

As one cannot distribute MSFS and/or Navigraph data via the application package the user must initiate the data collection and consolidation.

There is a program provided in the application package which does this chore.

→ Below in the Appendix find the chapter **Data Loader** and proceed accordingly

Content

Flight bag providing	1
Standalone Installation and Usage.....	3
Limitations	3
What is shown.....	3
Shelf Tab	4
Map Tab	5
Supported Map Providers.....	5
Map Display – Intentionally a zoomable but static map with decorations.....	6
Map – Ops.....	7
Airport / Area Information.....	8
Decorating the map	9
Aircraft tracking	9
Navaids	10
Airport VFR Marks.....	11
Selecting a runway for VFR or IFR approach waypoints decoration	11
Routes	12
METAR Tab	13
Perf. Tab.....	13
Profile Tab.....	14
Notes Tab	15
SimBrief Integration	16
MSFS Flightplan Integration.....	17
Airport Reports (new V0.67)	18
METAR Data Retrieval:	19
Distributed Contents:	19
Appendix:	19
File Storage	19
Settings Files and Reset Configuration	19
Map Data retrieval and storage disclaimer.....	19
Data Loader	20
Instances.....	21
Issue Reporting:	22

Standalone Installation and Usage

- Deploy the release all zip content in a folder (no installer provided or needed)

Best is to start MSFS first, then the Flight Bag (but the App should connect the sim in any case)

- Start MSFS2020 first and once the Main Menu is shown
- Start FS20_FlightBag.exe
- It attempts to connect to the Flight simulator in 5 sec intervals, but shows a red bar while it is not connected to MSFS
- Use the **Tabs** for Shelf, Map, METAR, Perf., Notes, and Config.
- To **Exit** and stop the program click the top right X mark


Limitations

Some aircraft do not provide or do not synchronize data with the Simulator as expected.

Such aircrafts maintain their own internal models and act properly but do not share or interact well with the generic simulation where the FlightBag takes the data from to track aircraft and selected airports.

What is shown

At startup there is an empty Shelf, Map, METAR, Perf., Notes, and Config. Tabs.



- Shelf provides a list of documents located in the selected folder
- Map shows a static map with various display options
- METAR allows to retrieve METAR information – if selected it translates the METAR string into something more readable.
- Perf. Lists Aircraft Performance numbers and Touchdown Data as reported from the Sim.
- Notes – a simple notepad area,
- Config. Allow to setup some options

See below for some of the items available

Shelf Tab

- The Window allows to choose from image or PDF files contained in a folder (new V0.67)
- An image can be zoomed in or out and dragged within the window
- Supported image file formats are PNG, JPG, GIF
- Supports subfolder browsing (new V0.67)

Tip: scale the image in a way that the resolution is high enough to read it properly at the most used zoom level, usually this is around 1400 pix on the longer side – but you may try and find what works best.

Configuration:

In order to use the Flight Bag you must select the folder where your images are located – go to **Config. Tab**



Default is the directory **DemoBag** in the App folder – supplied with some demo images in the App distribution.


Click '...' and choose any directory to use.

Usage:

The first time the window will open empty

– Click the **Book Shelf Icon** in the top left corner to load the documents (images)

First listed are subfolders (violet color) (new V0.67)




Click a subfolder to enter it. Click '..\ Leave subfolder' to return

From the list of documents **click** the one to display.

Zoom the document with the mouse **scroll wheel** or **click the +- icons** in the bottom right corner.

PDF documents will scroll with the wheel and zoom using Ctrl-Wheel or using +- Buttons (new V0.67)

Use the **left mouse click and drag** to move the document in the window.




Click right to reset the zoom and re-center the document.

Click the Book Shelf icon to select another document.

Resize the window as usual in Windows.

Hide the window with Hotkey, Context Menu or the X icon.

Example from the Demo included



Map Tab

Supported Map Providers

MapLib supports a fixed number of Map Tile Providers as well as 3 user defined ones.

→ **ALWAYS consider the terms of use for any of the map providers**

Free and open Tile services are at the time of writing – enabled by default

OpenStreetMap (OSM) and some derivatives

<https://www.openstreetmap.org>

OpenTopo, a 3d enhanced map from an open source project (usually rather slow to respond...).

<https://opentopomap.org>

Stadia Maps (require a registration now) (changed V0.67)

by Stamen 3D shaped terrain map (remote areas are rather slow to respond) – disabled by default

ChartBundle - for US regions only (FAA provides data at no cost, other countries do not...) – disabled by default

<https://www.chartbundle.com/charts/>

Go for the Appendix MapLib Document – INI File - below to see how to enable them.

Tile Services which need either a key or are subject to licensing terms – disabled by default

Bing Maps (Microsoft map service) needs a key and subject to licensing

<https://docs.microsoft.com/en-us/bingmaps/getting-started>

ESRI/ARCGIS Tile Services as part of their offering – subject to license, don't use if not licensed

<https://developers.arcgis.com/documentation/mapping-apis-and-services/data-hosting/services/image-tile-service/>

Remark:


Don't ask for Google Map support – I don't have a key and they are rather complicated to work with...

User defined tile services 1..6

You may have an own tile service running on your NAS or know a tile service you like to use.

Provider Configuration → Check the guide for MapLib (MapLib-Doc.pdf)

Map Display – Intentionally a zoomable but static map with decorations



The Map display intends to minimize the performance footprint and will only request tiles on user request.

There are 5 predefined ranges (XF=7, FF, F, M, N, C=15) which are loaded on demand and where the user can zoom in and out at discretion. *Note: decorations except the Route will be hidden above range FF.*


When in **AutoRange (AR) mode** it will zoom seamlessly between Z5 and Z15 levels of the map provider when zooming in or out.



When not in AutoRange mode (default) it will just zoom into the drawn image up to 20x magnification without switching to a more or less detailed map.

- The map is intentionally NOT a moving map. The user may shift the mapped area if desired.
- The map draws the selected airport runways if in sight and can be decorated with Navaids, VFR patterns, Aircraft
- The map displays and tracks the aircraft with some predefined essential data

Map – Ops



The map is Airport centric – i.e. usually you would have an airport selected.

Use Search Airport or click the DEP, ARR ICAO label to center the view on that airport (above it's YPPH)

While in flight you may move the shown map area using the mouse with left click or use the 'center aircraft' button once in a while to re-locate the map.

For the selected airport one can list runways, tower frequencies as well as the area navaids.

NOTE: for the time being the map may be a bit jumpy when moving it around rather fast. In the end it should show the expected area – if a yellow border remains, try to do a small move with the mouse.
(Work in progress to clean it up)

Airport / Area Information

Runway 22R - Approaches

ILS (NOLEN)	RWY 22R
LOC (NOLEN)	RWY 22R
RNAV (NOLEN)	RWY 22R

Airport - Runways

04L (039°)	2284x46 m - ASPHALT
22R (219°)	IRXZ 111.30 GS(3.0° 27 nm) 2284x46 m - ASPHALT
04R (041°)	IFJU 110.10 GS(3.0° 27 nm) 2458x46 m - ASPHALT
22L (221°)	ILQQ 110.10 GS(3.0° 27 nm) 2458x46 m - ASPHALT
09L (090°)	ISAJ 111.75 GS(3.0° 27 nm) 2284x46 m - ASPHALT
27R (270°)	IABU 111.75 GS(3.0° 27 nm) 2284x46 m - ASPHALT
09R (090°)	IJAV 110.50 GS(3.0° 27 nm) 3525x46 m - ASPHALT
27L (270°)	IIAC 110.50 GS(3.0° 27 nm) 3525x46 m - ASPHALT
10C (090°)	ISXH 108.95 GS(3.0° 27 nm) 3288x59 m - ASPHALT
28C (270°)	IVZE 108.95 GS(3.0° 27 nm) 3288x59 m - ASPHALT
10L (090°)	IMED 111.10 GS(3.0° 27 nm) 3960x46 m - ASPHALT
28R (270°)	ITSL 111.10 GS(3.0° 27 nm) 3960x46 m - ASPHALT
10R (090°)	IBYW 110.90 GS(3.0° 27 nm) 2279x53 m - ASPHALT
28L (270°)	IVQX 110.75 GS(3.0° 27 nm) 2279x53 m - ASPHALT
27C (270°)	IUYJ 111.90 GS(3.0° 27 nm) 3420x61 m - CEMENT
09C (090°)	IOYG 111.90 GS(3.0° 27 nm) 3420x61 m - CEMENT

Map tiles © OpenStreetMap contributors

Runway 22R - Approaches		
ILS (NOLEN)	RWY 22R	
LOC (NOLEN)	RWY 22R	
RNAV (NOLEN)	RWY 22R	

Approaches are shown as above, where the quote indicates that the data is from the Navigraph source. Such data is sometimes different or not available in the Sim. Above the LOC approach is from MS data and may not be available as separate chart in the Navigraph App.

Runway 22R
ILS OR LOC RWY 22R
21-11
RNAV (GPS) RWY 22R
22-11
Runway 27L

Clicking the Runway Icon will show/hide the list of airport runways found in the database.

If there is an ILS located for the runway the ILS ID, Frequency, GS angle and range is shown.

If there are Approaches for the selected runway found in the database it will show them above the runway panel as soon as you select (click) a runway.

Selecting (click) an Approach will show the Approach as Waypoint/Line decoration in the map

Selected items are highlighted (inverse coloring).

Airport - Frequencies

124.350 - CHICAGO (APPROACH)
125.700 - CHICAGO (APPROACH)
119.250 - OHARE (CLEARANCE)
119.250 - OHARE (CLEARANCE_PRE_TAXI)
121.600 - CHICAGO/O'HAREINTL (CLEARANCE_PRE_TAXI)
119.000 - CHICAGO (APPROACH)
133.625 - CHICAGO (APPROACH)
135.400 - KORD (ATIS)
121.600 - OHARE (CLEARANCE)
120.550 - CHICAGO (DEPARTURE)
125.000 - CHICAGO (DEPARTURE)
126.625 - CHICAGO (DEPARTURE)
128.200 - CHICAGO (DEPARTURE)
133.500 - CHICAGO (DEPARTURE)
118.050 - OHARESOUTH (GROUND)
121.675 - OHAREMETRERING (GROUND)
121.750 - OHARE (GROUND)
121.900 - OHARE (GROUND)
124.125 - OHARENORTH (GROUND)
128.000 - OHARE (GROUND)

Clicking the Tower Icon will show/hide the list of airport communication frequencies found in the database.

When there are many like at KORD it will turn into a scrollable list.

Area - Navaids

NDB GY 236.0 kHz (23 nm) GARIE
NDB IA 414.0 kHz (23 nm) CHICAGO OHA TAFFS
NDB ID 385.0 kHz (23 nm) CHICAGO OHA INDDY
NDB IK 272.0 kHz (23 nm) LUKOW
NDB OR 394.0 kHz (23 nm) CHSTR
NDB RV 257.0 kHz (23 nm) CHICAGO OHA JOCKY
NDB US 379.0 kHz (23 nm) WAUKE
NDB VP 212.0 kHz (38 nm) SEDLY
NDB VYS 230.0 kHz (38 nm) VALLEY
VOR DME BUU 114.50 MHz (38 nm) BURBUN
VOR DME CGT 114.20 MHz (60 nm) CHICAGO HEIGHTS
VOR DME DPA 168.48 MHz (60 nm) DUPAGE
VOR DME ENW 169.20 MHz (38 nm) KENOSHA
VOR DME EON 113.20 MHz (60 nm) PEOTONE
VOR DME GCO 168.25 MHz (60 nm) CHICAGO
VOR DME HRK 117.70 MHz (38 nm) HORLICK
VOR DME IKK 111.60 MHz (60 nm) KANKAKEE
VOR DME JOT 112.30 MHz (195 nm) JOLIET
VOR DME JVL 114.30 MHz (60 nm) JANEVILLE
VOR DME OKX 115.60 MHz (195 nm) KNOX
VOR DME RFD 110.80 MHz (60 nm) ROCKFORD

Map tiles © OpenStreetMap contributors

Clicking the Navaids Icon will show/hide the list of the mapped FF Area VOR/NDBs and frequencies found in the database when they are in signal range (new V0.67)

For each item the distance and direction from the aircraft and a signal level (A.F) is shown (new V0.67)

Note: Whether or not showing the Navaids on the map is part of decoration selection.


Decorating the map

- Map Lat/Lon Grid – toggles the grid
- Airport range circles (5, 15, 30, 60 nm radius)
- Aircraft tracking with some data points
- Route from SimBrief or MSFS Plans
- Navaids
- Airport VFR Markings
- Airports within the shown area (use Config. to select a minimum runway length)



Click to toggle visibility of the items

Aircraft tracking



When visible it will show the aircraft on the map if in the shown area, else it says 'aircraft out of sight'.

Data points are: (click an item to toggle either True/Mag or toggle Av/SI units

- True Heading (THDG) / Mag Heading (HDG)
- True Track (TTRK) / Mag Track (TRK)
- Altitude above MSL in ft / m
- RA in ft / m (<1500)
- IAS in kt / km/h
- GS in kt / km/h
- V/S in fpm / m/s

HDG : 320°	THDG: 320°
TTRK: 328°	TRK : 328°M
AMSL: 25'993 ft	AMSL: 7'923 m
IAS : 298 kt	IAS : 551 km/h
GS : 365 kt	GS : 675 km/h
V/S : +20 fpm	V/S : -0.1 m/s

The aircraft has a range feature which either shows 30° arcs at 2.5, 5, 10 nm out in light blue, the true ground track is marked with a 6° dark blue segment. These are TRUE degrees on the true north oriented map.




Under approach conditions the range marker changes to the expected ground contact at current IAS, VS and altitude which is shown as a green 20° arc (at the time of writing this feature needs some improvement...)




Wind speed and direction is shown as arrow with the speed label

The wind speed is default in kt but when changing units to SI it will be m/s




Navaids



VOR, DME, and NDB navaids are shown with ID and frequency at their location.

There is no further interaction available.

Waypoints for runway approaches can be shown if a runway **AND approach** is selected from the runway list.



Above the runway 26 and the LOC approach was selected (clicked), Approach waypoints with their assigned altitude found in the database are placed on the map.

Since V0.63 only the waypoints for the selected approach are shown also when Navaids are disabled (it allows for less clutter and more readable labels)

Also when selecting a runway a blue dotted line towards the runway is shown with steps at 2, 4, 8 and 16nm from the runway start.


Airport VFR Marks

Note: this feature may or may not please all kind of pilots – please let me know ...


Selecting a runway for VFR or IFR approach waypoints decoration

To **select** a runway get the Runway list and **click** one of the runways.

To **clear** the selection, click the 'Airports – Runways' text (hand appears) and the decorations will go away.




For a selected runway VFR marks are shown.



Above the runway 26 was selected (clicked)

To **select** an approach click the line item.

To **clear** the approach selection, click the 'Runway xy – Approaches' text (hand appears) and the decorations will go away.



When VFR marks is on and an approach is selected it looks like above.

Routes


Routes derived from SimBrief or MSFS Plan- or Flight files are shown when the Route icon is clicked.




A route is marked with magenta lines and circles, where legs belonging to a SID or STAR are shown in a darker magenta color as in the example right from waypoint APPLE to LANAK.

As long as there is no Approach information in a plan the last leg ends at the airport (ex. LANAK-> EGPF)

Requested plans from the Sim may eventually contain Approach information. Such data is created by the Sim ATC/Planner and the validity is sometimes questionable...



It is also dependent of the aircraft flown, some FMS do not share plans with the Sim internal systems and will therefore not provide any meaningful information in MSFS derived plans.



For any plan a flight table document is created in the Shelf (@.FlightTable). The table contains a row for each waypoint found in the plan together with some helpful information about the plan.

For SimBrief downloads the plan document @.FlightPlan is created and the images contained in the plan are downloaded if available and stored in Shelf.


To the right is the list of docs for a SimBrief download.

Note: plan documents are overwritten as soon as a new one is created or downloaded. But the currently viewed document does not change – select it again to view the most recent version.

@.FlightPlan
@.FlightTable
@.Route
@.SigWx 1 of 4
@.SigWx 2 of 4
@.SigWx 3 of 4
@.SigWx 4 of 4
@.UAD 1 of 3
@.UAD 2 of 3
@.UAD 3 of 3
@.Vertical profile

METAR Tab

This Tab will return METAR information for the station where the **Request** button was clicked.



Request - KORD:
KORD 141151Z 00000KT 10SM FEW250 15/11 A3010 RMK A02 SLP191 T01500111 10167 20144 53022
KORD @ Report Date 14. Time 11:51Z -
Altimeter: 30.10 inHg - 1019 hPa
Temp: 15°C (59°F) - Dewpoint: 11°C (52°F) (RH=77%)
Wind: calm
Visibility: 10.0 SM (16.1 km)
Clouds: few at 25'000 ft (AGL)
Flight Category: VFR (green)

If set in Config it will ‘translate’ the telegram into a more readable version as shown above.

If METAR does not provide data it might be that the service does not respond (try again in a few seconds) or the station is not available at all.

The ACFT will ask for a station based on the aircrafts LAT/LON position from the nearest weather station found within max. 500 Statute miles in direction of flight, the returned station is sometimes not really what one expects, but what the Metar server provides... (Cannot change it though).

The Metar is real weather information at the location i.e. suitable when using Live Weather.

– MSFS Sim weather cannot be retrieved outside the sim.

Perf. Tab

Performance data as reported from the Simulator.

Touchdown data as reported from the Simulator.

There is a Touchdown log saved (MyDocuments\MSFS_HudBarSave\TouchDownLog.csv) when using the FlightBag

	Aircraft	Callsign	Date_Time	VRate_fpm	Pitch_deg	Bank_deg	Hdg_deg_m	RwyLatDev_ft	RwyLonDev_ft
2	Cessna Skyhawk G1000 Asobo	BM98-CH	2022-10-16T18:25:06	4.8	0	0	274	NaN	NaN
3	Cessna Skyhawk G1000 Asobo	BM98-CH	2022-10-16T18:28:33	88.6	-2.7	-1.2	78	NaN	NaN
4	Cessna Skyhawk G1000 Asobo	BM98-CH	2022-10-18T01:09:36	5.7	0	0	274	2664.9	-15406.1
5	Cessna Skyhawk G1000 Asobo	BM98-CH	2022-10-18T01:11:49	144.8	-1.7	0.7	78	3.7	199.2
5	Cessna CJ4 Citation Asobo	BM98-CH	2022-10-18T01:33:04	8	-3.6	-0.3	152	NaN	NaN
7	Cessna CJ4 Citation Asobo	BM98-CH	2022-10-18T01:47:34	306.9	-2.7	0.6	94	-1.4	-909
3	Cessna CJ4 Citation Asobo	BM98-CH	2022-10-18T02:00:39	200.2	-2.4	-1.3	96	5.8	-848
9	Cessna Skyhawk G1000 Asobo	BM98-CH	2022-10-19T14:10:34	6	0	0	274	3307.9	-15702.9
0	HJET HA420 Dark Blue Stripes	BM98-CH	2022-10-19T14:50:42	0	0	0	318	2952.7	-15285.4

You may find Runway Deviation sometimes NaN or off by miles. The deviation is derived from the ATC assumed runway – which sometimes is just not set (NaN) or is still the starting runway (number is far off).

Also when you bump at the takeoff (happens...) you see most likely a separate line with a small number for the VRate (e.g. line 2)

Profile Tab

An interactive profile table – using the “Rule of 3” as base.

FPA	IAS	TAS	GS	VS	Altitude	Dist [nm]
3.3	242	348	347	1980	23434	
Profile %	%	IAS/ft	GS/ft	VS/ft/min	Alt [ft]	Dist [nm]
0.4	0.7	40	600	4'600	45'000	57
0.6	1.0	60	580	4'450	40'000	45
0.8	1.3	80	560	4'300	38'000	41
1.0	1.7	100	540	4'150	36'000	36
1.2	2.1	120	520	4'000	34'000	32
1.4	2.4	140	500	3'850	32'000	27
1.6	2.8	160	480	3'700	30'000	23
1.8	3.1	180	460	3'550	28'000	18
2.0	3.5	200	440	3'400	26'000	14
2.2	3.8	220	420	3'250	24'000	9
2.4	4.2	240	400	3'100	22'000	5
2.6	4.5	260	380	2'950	20'000	0
2.8	4.9	280	360	2'800	18'000	5
3.0	5.2	300	340	2'650	16'000	9
3.2	5.6	320	320	2'450	15'000	11
3.4	5.9	340	300	2'300	14'000	14
3.6	6.3	360	280	2'150	13'000	16
3.8	6.6	380	260	2'000	12'000	18
4.0	7.0	400	240	1'850	11'000	20
4.2	7.3	420	220	1'700	10'000	23
4.4	7.7	440	200	1'550	9'000	25
4.6	8.0	460	180	1'400	8'000	27
4.8	8.4	480	160	1'250	7'000	29
5.0	8.7	500	140	1'100	6'000	33
5.2	9.1	520	120	9'500	5'000	34
5.4	9.5	540	100	7'50	4'000	36
5.6	9.8	560	80	6'000	3'000	39
5.8	10.2	580	60	4'500	2'000	41
6.0	10.5	600	40	3'000	1'000	43
					0	45

Above the tables are the current numbers as reported from the Simulator:

FPA is the current flight path angle then IAS, TAS, GS, VS, and Altitude (in kts and Alt in ft)

The current FPA, GS, and Altitude values are highlighted in the respective tables with a greenish color (for values in between row values for GS and Alt the higher one is marked in order to provide a safety margin).

Click a flight profile row in the left table - it will recalculate the 2nd and 3rd table.

The middle table shows the required vertical speed at a given **ground speed** (GS) in order to maintain the profile. E.g. above to maintain a 4.4° profile at GS of 260 kts it asks for 2000 ft/min vertical rate.

Clicking a row in the middle table serves only as mark or reminder and will not change any value.

The right table shows the distance which is flown to get to a certain altitude at the selected profile angle. E.g. starting from FL200 with a 4.4° profile it needs 23nm to get either down to FL100 or up to FL300.

Note: add a safety margin to the calculated distances!

Clicking a row in the right table will set this altitude as zero distance and calculate from there up and down.

There are no signed numbers in the tables, it's meant as either climb or descend.

Example:

We are at 26'000 ft with a GS of 480 as the greenish marks are showing, above the table are the real-time values from the Sim.

The plane is heading down at 2.4° and this profile is currently selected - showing a VS of ~2000 ft/min is required and flown.

Below the left screen has 26'000 ft selected as starting point and the distances are calculated up and down. To get down to 7'000 ft it shows we need about 79nm.

In the middle screen the new target altitude of 7'000 ft is selected and it shows the remaining distance as the green mark walks down while we descend. Also showing the needed distance to the airfield which is at about 1'000ft – it would be 25nm when flying at 2.4°.

In the right screen the approach profile of 3° is selected and now the VS has changed but also the distance from 7000 to 1000ft is back to 20nm for the steeper approach (now we only need to get our speed back in time and maintain the profiles..)

FPA	IAS	TAS	GS	VS	Altitude	Dist [nm]
-2.4	331	471	472	1980	24'622	
Profile %	%	IAS/ft	GS/ft	VS/ft/min	Alt [ft]	Dist [nm]
0.4	0.7	40	600	2'500	45'000	57
0.6	1.0	60	580	2'450	40'000	45
0.8	1.3	80	560	2'350	38'000	41
1.0	1.7	100	540	2'250	36'000	36
1.2	2.1	120	520	2'200	34'000	33
1.4	2.4	140	500	2'150	32'000	25
1.6	2.8	160	480	2'000	30'000	17
1.8	3.1	180	460	1'950	28'000	8
2.0	3.5	200	440	1'850	26'000	0
2.2	3.8	220	420	1'750	24'000	17
2.4	4.2	240	400	1'700	22'000	33
2.6	4.5	260	380	1'600	20'000	25
2.8	4.9	280	360	1'500	18'000	33
3.0	5.2	300	340	1'400	16'000	42
3.2	5.6	320	320	1'300	15'000	33
3.4	5.9	340	300	1'200	14'000	29
3.6	6.3	360	280	1'150	13'000	25
3.8	6.6	380	260	1'100	12'000	21
4.0	7.0	400	240	1'000	11'000	17
4.2	7.3	420	220	900	10'000	13
4.4	7.7	440	200	850	9'000	8
4.6	8.0	460	180	750	8'000	4
4.8	8.4	480	160	650	7'000	0
5.0	8.7	500	140	600	6'000	4
5.2	9.1	520	120	500	5'000	8
5.4	9.5	540	100	400	4'000	13
5.6	9.8	560	80	350	3'000	17
5.8	10.2	580	60	250	2'000	100
6.0	10.5	600	40	150	1'000	25
					0	188

FPA	IAS	TAS	GS	VS	Altitude	Dist [nm]
-2.4	331	469	472	2'000	24'361	
Profile %	%	IAS/ft	GS/ft	VS/ft/min	Alt [ft]	Dist [nm]
0.4	0.7	40	600	2'450	45'000	158
0.6	1.0	60	580	2'450	40'000	138
0.8	1.3	80	560	2'350	38'000	103
1.0	1.7	100	540	2'250	36'000	97
1.2	2.1	120	520	2'200	34'000	86
1.4	2.4	140	500	2'100	32'000	104
1.6	2.8	160	480	2'000	30'000	96
1.8	3.1	180	460	1'950	28'000	88
2.0	3.5	200	440	1'850	26'000	79
2.2	3.8	220	420	1'750	24'000	71
2.4	4.2	240	400	1'700	22'000	63
2.6	4.5	260	380	1'600	20'000	54
2.8	4.9	280	360	1'500	18'000	46
3.0	5.2	300	340	1'450	16'000	38
3.2	5.6	320	320	1'350	15'000	33
3.4	5.9	340	300	1'250	14'000	29
3.6	6.3	360	280	1'150	13'000	25
3.8	6.6	380	260	1'100	12'000	21
4.0	7.0	400	240	1'000	11'000	17
4.2	7.3	420	220	900	10'000	13
4.4	7.7	440	200	850	9'000	8
4.6	8.0	460	180	750	8'000	4
4.8	8.4	480	160	650	7'000	0
5.0	8.7	500	140	600	6'000	4
5.2	9.1	520	120	500	5'000	8
5.4	9.5	540	100	400	4'000	13
5.6	9.8	560	80	350	3'000	17
5.8	10.2	580	60	250	2'000	100
6.0	10.5	600	40	150	1'000	25
					0	28

FPA	IAS	TAS	GS	VS	Altitude	Dist [nm]
-2.5	330	466	467	-2'020	24'005	
Profile %	%	IAS/ft	GS/ft	VS/ft/min	Alt [ft]	Dist [nm]
0.4	0.7	40	600	3'150	45'000	127
0.6	1.0	60	580	3'050	40'000	110
0.8	1.3	80	560	2'950	38'000	103
1.0	1.7	100	540	2'900	36'000	97
1.2	2.1	120	520	2'750	34'000	86
1.4	2.4	140	500	2'600	32'000	103
1.6	2.8	160	480	2'500	30'000	77
1.8	3.1	180	460	2'400	28'000	78
2.0	3.5	200	440	2'300	26'000	63
2.2	3.8	220	420	2'200	24'000	57
2.4	4.2	240	400	2'100	22'000	50
2.6	4.5	260	380	2'000	20'000	43
2.8	4.9	280	360	1'900	18'000	37
3.0	5.2	300	340	1'800	16'000	30
3.2	5.6	320	320	1'700	15'000	27
3.4	5.9	340	300	1'600	14'000	23
3.6	6.3	360	280	1'450	13'000	20
3.8	6.6	380	260	1'350	12'000	17
4.0	7.0	400	240	1'250	11'000	13
4.2	7.3	420	220	1'150	10'000	10
4.4	7.7	440	200	1'050	9'000	7
4.6	8.0	460	180	950	8'000	3
4.8	8.4	480	160	850	7'000	0
5.0	8.7	500	140	750	6'000	3
5.2	9.1	520	120	650	5'000	7
5.4	9.5	540	100	500	4'000	10
5.6	9.8	560	80	350	3'000	13
5.8	10.2	580	60	250	2'000	17
6.0	10.5	600	40	150	1'000	28
					0	23

Can be used to estimate the TOD or to check if a constraint can be made with the current profile.


Notes Tab

just a notepad which is saved when closing the App

Config Tab

Set the desired **Departure and Arrival Airports**

Enter the ICAO code and hit the Enter key – if the airport is found it will turn green and the common name is shown right to it, else it will turn red, indicating that ICAO code was not found in the database.



Map Decorations:

Min. Runway length for Alt. Airports' lets you select the minimum length for any runway an airport must have in order to be shown when Airports decoration is ON. Choose a min length from the drop down.

Checked 'Show Aircraft range arcs' will show the leading arcs of the tracked aircraft when Aircraft decoration is ON.

Checked 'Show Aircraft tracking dots' will show the trailing dots of the current tracked aircraft when Aircraft decoration is ON.

Checked 'Show Aircraft Wind arrow' will show an arrow of wind direction and the speed of the wind around the aircraft.

SimBrief:

Enter your SimBrief PilotID (a 2..7 digit number), hit Return to validate it (once – it will be stored in Settings)

Then click "Load Plan" to retrieve your latest Flight Plan – it will reply the Departure and Arrival Airport and also fill in the corresponding fields above.

MSFS Flightplan:

Select a PLN, FLT or LNM or GPX file from the disk, request the ATC plan from the Sim or load the default plan from MS to load a route and create a Plan Table document in the Shelf. (added V0.67)

METAR:

Checked 'Add 'readable' METAR will show the more readable METAR information along with the received telegram.

Shelf:

Shelf Folder Location: click the button <...> to select a folder where the images for the Shelf Tab can be found.

→ The Configuration is shared for the standalone and the HudBar version of the FlightBag.

SimBrief Integration


If you are using SimBrief for your flight planning you may retrieve the latest plan and some documents now.

simBrief by Navigraph

First provide your Pilot ID (a 2..7 digit number) in Configuration, it will be stored in Settings.

Use “Load Plan” in Configuration to retrieve the last plan data.

Once successful a Flight Plan document is stored in the Shelf together with the pictures created by SimBrief.




In Shelf you will find the documents starting with **@. ...** (e.g. @.FlightPlan, @.FlightTable, etc)

@.FlightPlan is the main plan where the long NOTAM and image sections have been stripped from.

It is stored as one Image document and can be read, zoomed and scrolled like any other **PDF** doc. (new V0.67)

For the Map display the planned route is shown (can be toggled on and off) using this button:



While the route is shown as magenta line the waypoints are circles with the ID below.

Note:

The plan does not include approaches and therefore the last segment is usually pointing at the airport, rather than the approach path.


In the example the plan is to land on runway 27. With the VFR runway display one has at least a rough overview of the approach pattern needed.

Note: There are some settings in SimBrief which may disable the availability of images in the download, check SimBrief Settings for details.

MSFS Flightplan Integration

In Config you may load either the default MSFS Plan (CUSTOMFLIGHT.PLN in the MISSIONS folder) or request the most current Simulation ATC FLT plan or select a PLN, FLT, LNMP or GPX Flightplan file from any location on the computer. (added V0.67)

MS Plans will load the route and also a flight plan in table format is created and saved in the Shelf the name is: `@.FlightTable`



IFR Flightplan from (KLAS) Las Vegas - Mc Carren Intl to (KSLC) Salt Lake City Intl

IFR Plan, routing is HighAlt, initial cruise altitude: 26'000 ft - steps: KLAS/0260

Depart using SID GIDGT2 from Runway RW01R (elev 2'114 ft)

Arrive using STAR LEEHYS


Approach through ILS RW16R and land on Runway RW16R (elev 4'226 ft)

Ident	Alt ft	Type	Proc/Info	Trk °M	Dist nm	Remaining nm
KLAS	2'181	AIRPORT		011		512.1
RW01R	2'181	RUNWAY		255	0.8	511.3
AUTOWP1	4'000	USER		035	3.4	507.8
KYBAD	8'600	WAYPOINT		093	8.7	499.1
HAIND	10'700	WAYPOINT		093	4.1	495.0
ARRO	11'500	WAYPOINT	SID GIDGT2	094	8.5	486.5
GIDGT	11'500	WAYPOINT	SID GIDGT2	095	22.5	464.1
GEEOO	26'000	WAYPOINT		074	33.5	430.6
BETHL	26'000	WAYPOINT		074	62.8	367.7
VERKN	26'000	WAYPOINT		040	34.8	333.0
ROCCY	26'000	WAYPOINT		017	27.0	306.0
SARAF	26'000	WAYPOINT	via Awy Q96	058	70.0	236.0
ADIBE	26'000	WAYPOINT		023	31.1	204.9
FOSOV	26'000	WAYPOINT		007	18.0	186.8
HELPY	26'000	WAYPOINT		033	22.9	163.9
GOSHU	26'000	WAYPOINT		306	36.4	127.5

The above is from a flight planned in LittleNavMap where the MSFS (PLN) file was saved and loaded in Config Select & Load Plan...

The XF Range allows a larger overview of such a plan.


MSFS Flightplan:
Select & Load Plan...



Note: You may use both SimBrief and MSFS Plan loading without having the Simulator running.


Airport Reports (new V0.67)

Tabular reports for airports are available in the 'Airport Reports' folder.



An Airport Report is newly created each time you enter a valid airport ICAO in the Finder field and hit Enter or click the airport icon.

An Airport Report is created as PDF document.



Airport Reports include 6 sections:

- ICAO + IATA when available, Name + coordinates
- Runways + their Approaches
- SID Procedures per runway
- STAR Procedures per runway
- Communication Frequencies
- Navaids in range

Arrows indicate the direction of the aircraft with regards to the airport i.e. 'outgoing towards' for runways and SIDs, 'incoming from' for STARs

Sections might be empty if there is no such information available.

A report is overwritten when a new one for the same airport is created.

Note: you need to re-open a document when the same was opened while creating a new report.

Same as with any document in the Shelf.

The screenshot shows the 'Map' tab of the MSFS FlightBag application, displaying detailed airport reports for RJAH. The reports are organized into sections: Runways, SID Procedures, and STAR Procedures. The Runways section shows data for RWY 019' (RW03L, RW03R, RW21L, RW21R) and RWY 199' (RW03L, RW03R, RW21L, RW21R). The SID Procedures section shows data for RWY 019' (RW03L, RW03R, RW21L, RW21R) and RWY 199' (RW03L, RW03R, RW21L, RW21R). The STAR Procedures section shows data for RWY 019' (RW03L, RW03R, RW21L, RW21R) and RWY 199' (RW03L, RW03R, RW21L, RW21R). The reports include columns for RWY, HDG, Dim [ft], Dim [m], Surface, and Transitions.

METAR Data Retrieval:

Please note that the program will issue HTTP Requests to an external server to retrieve the latest METAR information.

The data for METAR is retrieved from: <https://aviationweather.gov>

Please make sure to comply with their terms and conditions when retrieving METAR data with this program.

URL is updated now (updated V0.67)

Distributed Contents:

My FlightSim Libraries (included in the release package)

SEE README.TXT FOR THE LIST

CoordLib is based on: <https://github.com/chrisveness/geodesy>

Translated to C# and partially modified

Original code license: The MIT License (MIT)

Appendix:

File Storage

Files are generally stored in the “<MyDocuments>\MSFS_HudBarSave” folder

Settings Files and Reset Configuration

The configuration is stored in using a Json AppSettings Library.

The configuration can be found here: <MyDocuments>\MSFS_HudBarSave\settings\<APP>

For the Flight Bag, the settings file is: **FShelfAppSettings.json**

This file stores your configuration but I suggest to not edit it – unless you know what to change, it may prevent the program from starting if done wrongly.

If you find something really wrong – you may backup and delete the settings file and the program will use the defaults to start with.

Map Data retrieval and storage disclaimer

Map cache files:

The map cache files can be found here: <MyDocuments>\MSFS_HudBarSave\cache\<Provider>.dblite

MapLib retrieves tiles only for the user requested location and zoom level.

The visualization WinForms UserControl **bm98_Map** requests tiles as a matrix of 8x8 tiles at zoom levels for the 6 different ranges: XF=7, FF= 9, F=11, M= 12, N=13, C=15

With **AutoRange** enabled it will load tiles from zoom level 5 to 15 when zooming the Map



MapLib stores tiles per provider in a computer local disk cache and will clean up tiles older than 100 days or when the providers cache exceeds ~128MB / ~5120 tiles at startup of the application.

The cache size can be set from 32..1024 MB (see MapLib document in the Appendix) (new V067)

MapLib maintains a memory cache for 800 tiles (about 20MB RAM) while an application is running.

→ If you encounter incorrect tiles or other oddities – first delete the cache files and try again.


Provider Configuration → Check the guide for MapLib (MapLib-Doc.pdf – at the end of this document)

Download task complies with OSM policy i.e. only 2 concurrent threads.

Data Loader

Go for the application folder and then into the subfolder \dataLoader

Run FacilityDataLoader.exe:



First check if the program finds the MSFS data path.

It does follow the MS specs for Store and Steam but...

If not you may need to use Change Path.. to point it to the folder (where Community and Official folders can be found)

V0.67 Sourcing from LNM is currently unavailable ~~If the LittleNavMap database is found it will show it as well.~~

You may choose the source for the data, either collecting from the MS files where you may include Community content and/or Navigraph (if installed)

Check the sources.

Then hit Start Process and have some patience.

The program will report progress and once it finished its data collection it will tell you.

V0.67 To serve all new functionality of the FlightBag a lot more data is collected and the size has increased to **450MB**. The database is new V2 (fs2020genAptv2.dblite), the old one is not deleted.

The database is stored at `MyDocuments\MSFS_HudBarSave\db\fs2020genAptv2.dblite` and is about 450MB.

REDO this process when either a new Navigraph version is out and when MS provides substantial updates.

Instances

You may want to start the FlightBag more than once or get independent configurations and therefore programs running.

However they share the same Settings i.e. the location is saved from the last movement on any of the instances. In order to have truly independent instances with their own settings (all settings in Config and locations etc.) an Instance Name can be added to the Command Line when starting the FlightBag.

No command line parameter is considered and referred to as 'Default'

If you provide an Instance name to start the FlightBag it will be shown in the Window Title (Window Bar and Configuration)

You may start instances the easy way by creating a **Desktop Shortcut** and then modify the **Properties** of the **Shortcut** (right click) by adding an Instance name to the **Target** field:

This is the command line; add a space and the name at the end of the text field

Then may be rename the **Shortcut** in order to recognize it later.

Issue Reporting:

In case you encounter a problem please include as much information as possible. Sometimes it is also relevant which aircraft you were using.

Issues can be reported directly via GitHub (or a Message in Flightsim.to)

https://github.com/bm98/FS20_HudBar/issues

<https://flightsim.to/file/41426/msfs-flightbag>

For issues with a flight plans – the App stores the most recent version in

MyDocuments\MSFS_HudBarSave as file with the name **LastPlanDownload.XYZ**

PLEASE trigger the request again and then immediately save and include the files when reporting errors.

Enable Logging: In the application folder **copy** 'NLog.config.OFF' to 'NLog.config'

Logging will create generations of 'FS20_FlightBag.log' or 'FS20_HudBar.log' which might be useful to resolve issues

Disable Logging: Delete the 'NLog.config' file

Known Issues:

Stutter when requesting a Plan from Sim

The Simulator may stutter for a moment when requesting a plan download- seems to be an ASOBO/MS issue since long ago. Cannot do anything about it...

Settings are not stored or runtime exceptions

We have seen issues when Windows Protected Folders are enabled.

(<https://www.tenforums.com/tutorials/87858-add-protected-folders-controlled-folder-access-windows-10-a.html>)

In such a case Windows may deny programs which are not installed via MSI Installer access to write or delete files in some places, among them is the MyDocuments folder.

There is a check at the very beginning of the App which is trying to elaborate if such protection exists or not. If yes there is a MessageBox popping up related to Access Permission Error and the reason should be reported in the box.

In such a case first try to find out if protected folders are enabled and then add the FlightBag App to the list of allowed programs and start the program again to see if the problem persists – if it is still there head for Issue Reporting above.

(<https://support.microsoft.com/en-us/windows/allow-an-app-to-access-controlled-folders-b5b6627a-b008-2ca2-7931-7e51e912b034>)

MapLib – Map tile retrieval library

© 2023 - M.Burri

Nov 2023 Update see notes below marked with **Nov23**

Supported Map Providers

MapLib supports a fixed number of Map Tile Providers as well as 6 user defined ones.

→ **ALWAYS consider the terms of use for any of the map providers**

Free and open Tile services are at the time of writing – enabled by default

OpenStreetMap (OSM) and some derivatives

<https://www.openstreetmap.org>

OpenTopo, a 3d enhanced map from an open source project.

<https://opentopomap.org>

Nov23 Stadiamaps.com / STAMEN TERRAIN – disabled by default

Stamen 3D shaped terrain map is now served by Stadia Maps and **requires a Key** (a free subscription exists) therefore Stamen is now default Disabled, URLs have been updated, see below how to enable it

<https://stadiamaps.com/stamen/>

ChartBundle.com – disabled by default

<https://www.chartbundle.com/charts/>

Free aviation charts with limited coverage (FAA airspace)

Tile Services which need either a key or are subject to licensing terms – disabled by default

Bing Maps (Microsoft map service) needs a key and subject to licensing

<https://docs.microsoft.com/en-us/bingmaps/getting-started>

ESRI/ARCGIS Tile Services as part of their offering – subject to license, don't use if not licensed

<https://developers.arcgis.com/documentation/mapping-apis-and-services/data-hosting/services/image-tile-service/>

Remark:

Don't ask for Google Map support – I don't have a key and they are rather complicated to work with...

User defined tile services 1..6

You may have an own tile service running on your NAS or know a tile service you like to use.

The URL to be provided looks like:

Http=https://ip_or_address/route/{z}/{y}/{x}.imageformat

Where the {z} {y} {x} parts will be replaced by the requested zoom and coordinates.

The library expects a Mercator Tile Set with 0/0 top left tile number and 256x256 sized tiles – PNG and JPG image formats are supported.

Example:

Http=https://myNas:23356/tiles/{z}/{y}/{x}.jpg

Data retrieval and storage disclaimer

MapLib retrieves tiles only for the user requested location and zoom level.

The visualization WinForms UserControl **bm98_Map** requests tiles as a matrix of 8x8 tiles at zoom levels for the 5 different ranges: XF=7, FF= 9, F=11, M= 12, N=13, C=15

With AutoRange enabled it will load tiles from zoom level 6 to 15 when zooming the Map

MapLib stores tiles per provider in a computer local disk cache and will clean up tiles older than 100 days or when the providers cache exceeds the size limit at startup of the application.

Nov23 You may define a Disk Cache size from 32MB to 1024MB using the Ini file (see below)

Default is ~128MB / ~5120 tiles

MapLib maintains a memory cache for 800 tiles (about 20 MB RAM) while an application is running.

→ If you encounter incorrect tiles or other oddities – first delete the cache files and try again.

The download task will comply with OSM policy i.e. only 2 concurrent tile download threads.

INI File

Configuration goes via an **INI File** (`MapLibProvider.ini`) located per default in the **Applications directory**.

IF the Library finds a `MapLibProvider.ini` file in a user folder (`MyDocuments\MSFS_HudBarsSave`) it takes preference over the default one.

I.e. if you change INI settings, first copy the original file to this folder and make changes there, else it will be overwritten when extracting a new version from the Zip file

- The INI file consists of the Main section + a number of Provider sections
- INI files consists of lines where everything after a semicolon `<;>` is considered as comment.
- INI files do have a Keyword and a content in the form of: Keyword=Content
- INI files do have sections which start with a bracketed Name: [Section]
- The part of the INI file which is not lead by a section name is the Main Section

→ INI files are text files, use **only** Notepad or similar editors, never Word or other text processing programs to edit it's content

Main Section

`DefaultProvider= ..` → Default Provider and tiles the Map starts with

Use any of the enabled [ProviderNames] found in the later sections Use the exact name, or uncomment the template ones, only the first entry in the file is considered.

Example:

`DefaultProvider=OSM_OpenStreetMap`

`BingKey= ..` → A Key to use Bing Maps (see remark below)

A rather large number of characters provided by BING Maps in order to access their map services, visit URLs below at Microsoft

<https://docs.microsoft.com/en-us/bingmaps/getting-started>

<https://docs.microsoft.com/en-us/bingmaps/getting-started/bing-maps-dev-center-help/getting-a-bing-maps-key>

`StadiaStamenKey= ..` → A Key to use Stamen Maps (see remark below) **Nov23**

A rather large number of characters provided by Stadia Maps in order to access their map services, visit URLs below at Stadia Maps

<https://stadiamaps.com/stamen/>

`DiskCacheMB=128` → A number 32..1024 to set the disk cache size in MB per provider (128 default) **Nov23**

Provider Sections:

[ProviderName]	→ Provider name – don't change , the library expects those names
Name=...	→ The name shown in the selection list
Enabled=...	→ True if the provider is enabled else False To enable a provider set this entry to True, to disable use False Enabled providers will show up in the map selection to choose from. The free providers are enabled in the INI file, not so free ones and chartbundle disabled.

Example:

Enabled=True

Http=...	→ The map tile server address, most don't need an entry and are listed as comment for reference. For OSM one could use a variety of specialized servers in order to get e.g. names in another language than OSM provides them, e.g. the .de server will supply translated city names for parts of Asia. For the User Entries see below.
----------	---

Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat

Where the {z} {x} {y} parts will be replaced by the requested zoom and coordinates.


The library expects a Mercator Tile Set with 0/0 top left tile number and 256x256 sized tiles – PNG and JPG image formats are supported.

Example: see above

Data Loader

Go for the application folder and then into the subfolder \dataLoader

Run FacilityDataLoader.exe:



First check if the program finds the MSFS data path.

It does follow the MS specs for Store and Steam but...

If not you may need to use Change Path.. to point it to the folder (where Community and Official folders can be found)

Nov23 Sourcing from LNM is currently unavailable ~~If the LittleNavMap database is found it will show it as well.~~

You may choose the source for the data, either collecting from the MS files where you may include Community content and/or Navigraph (if installed)

Check the sources.

Then hit Start Process and have some patience.

The program will report progress and once it finished its data collection it will tell you.

Nov23 To serve all new functionality of the FlightBag a lot more data is collected and the size has increased to 450MB. The database is new V2 (fs2020genAptV2.dbLite), the old one is not deleted.

The database is stored at MyDocuments\MSFS_HudBarSave\db\fs2020genAptV2.dbLite and is about 450MB.

REDO this process when either a new Navigraph version is out and when MS provides substantial updates.

APPENDIX (default INI File):

```
; MapLib Provider Overrides
;
; Format:
; /// DefaultProvider=PROVIDER
; /// BingKey=KEY
; ///
; /// [PROVIDER]
; /// Name=a name
; /// Enabled=true / false
; /// Http=URL
;
; Text after a semicolon is treated as comment
;
;=> File name must be 'MapLibProvider.ini'
;
; Define the DefaultProvider from the [PROVIDER] names
;
; In each providers section:
; Set 'Enabled=true' to be able to use it
; Change Name=new name if you don't like it
;
; Uncomment 'Http=http....' to override the URL used to retrieve map tiles
; -> If unsure, leave it alone (The App may break or not respond any longer)
;
; For URLs:
; There are 3 placeholders for {x},{y},{z} (xy tile coords + zoom)
; When multiple server subdomains are available - {s} can be used
; For some you need an access key (personal, subscription etc)
; Key=sadfsdfsdf
;
; NOTE there is no privacy or protection when typing the key here
; the key is only used in the tile loading HTTP request as per provider guidance
;
;
; Default Provider to use => one of the Provider Chapter IDs ([NAME] from below)
DefaultProvider=OSM_OpenStreetMap ; OSM_OpenStreetMap is the free default provider

;DefaultProvider=OpenTopo

; Here comes your Bing Map Key if you want to use Bing Maps
BingKey=<YOUR KEY>

; Here comes your Stadia Key for Stamen Maps
StadiaStamenKey=<YOUR KEY>

; Disk Cache per Provider in MB default 128MB (from 32 to 1024 max)
; Remove semicolon to enable your setting
;DiskCacheMB=128

; PROVIDER SECTIONS

[OSM_OpenStreetMap]
; OpenStreetMap (see terms of use before using it)
Name=OSM OpenStreetMap
Enabled=true ; should never be disabled
;Http=https://(s).tile.openstreetmap.org/{z}/{x}/{y}.png ; default, labeled according to the region (e.g. Japanese etc)
;Http=https://(s).tile.openstreetmap.de/{z}/{x}/{y}.png ; adds translated names to the local ones
;Http=https://(s).tile.openstreetmap.fr/osmfr/{z}/{x}/{y}.png ; focus on french translation; international items are partly translated

[OpenTopo]
; Street Map 3D enhanced
; OpenTopo (see terms of use before using it)
Name=OpenTopo
Enabled=true
;Http=https://(s).tile.opentopomap.org/{z}/{x}/{y}.png ; default
;Http=https://a.tile.opentopomap.org/{z}/{x}/{y}.png ; without subdomain

[Stamen_Terrain]
; Street Map 3D shaped
; NEW Oct.2023 served by Stadia - needs a Key see
; https://docs.stadiamaps.com (see terms of use before using it)
Name=Stamen 3D Street Map
Enabled=false
;Http=https://tiles.stadiamaps.com/tiles/stamen_terrain/{z}/{x}/{y}.png?api_key=YOUR-API-KEY

; ****
; From http://www.chartbundle.com/charts/ see terms of use
; For US regions only (FAA provides data at no cost, other countries do not...)
; Disabled per default - change: Enabled=true to get the ones you need
; ****
[CB_SEC]
; Sectional Charts
Name=CB Sectional Charts
Enabled=false
;Http=https://wms.chartbundle.com/tms/1.0.0/sec/{z}/{x}/{y}.png?origin=nw ; default

[CB_TAC]
; Terminal Area Charts
Name=CB Terminal Area Charts
```

```

Enabled=false
;Http=https://wms.chartbundle.com/tms/1.0.0/tac/{z}/{x}/{y}.png?origin=nw ; default

[CB_ENRA]
; IFR Area Charts
Name=CB IFR Area Charts
Enabled=false
;Http=https://wms.chartbundle.com/tms/1.0.0/enra/{z}/{x}/{y}.png?origin=nw ; default

[CB_ENRL]
; IFR Enroute Low Charts
Name=CB IFR Enroute Low Charts
Enabled=false
;Http=https://wms.chartbundle.com/tms/1.0.0/enrl/{z}/{x}/{y}.png?origin=nw ; default

[CB_ENRH]
; IFR Enroute High Charts
Name=CB IFR Enroute High Charts
Enabled=false
;Http=https://wms.chartbundle.com/tms/1.0.0/enrh/{z}/{x}/{y}.png?origin=nw ; default

; ****
; Microsoft Bing MAPS (needs a Key to access -> https://www.microsoft.com/en-us/maps/create-a-bing-maps-key)
; ****
; Note: Bing URLs are retrieved dynamically and changing the Provider here has no effect (for reference only)

[Bing_Imagery]
; Satellite Imagery
Name=Bing Satellite Imagery
Enabled=false
;Http=https://ecn.{subdomain}.tiles.virtualearth.net/tiles/a{quadkey}.jpeg?g=12552 ; not used, for reference only

[Bing_ImageryLabels]
; Satellite Imagery with road labels
Name=Bing Satellite Imagery w. Labels
Enabled=false
;Http=https://ecn.{subdomain}.tiles.virtualearth.net/tiles/h{quadkey}.jpeg?g=12552&mkt={culture} ; not used, for reference only

[Bing_OStreetMap]
; Street Map
Name=Bing OSM StreetMap
Enabled=false
;Http=https://ecn.{subdomain}.tiles.virtualearth.net/tiles/r{quadkey}.jpeg?g=12552&mkt={culture}&shading=hill ; not used, for reference only

; ****
; ESRI/ARCGIS Maps (subject to terms of use - your at your own here...)
; ****

[ESRI_Imagery]
; Satellite Imagery
; ESRI/ARCGIS World Imagery (see terms of use before using it)
Name=ESRI/ARCGIS World Imagery
Enabled=false
;Http=https://services.arcgisonline.com/arcgis/rest/services/World_Imagery/MapServer/tile/{z}/{y}/{x} ; default

[ESRI_StreetMap]
; Street Map
; ESRI/ARCGIS StreetMap (see terms of use before using it)
Name=ESRI/ARCGIS StreetMap
Enabled=false
;Http=https://services.arcgisonline.com/arcgis/rest/services/World_Street_Map/MapServer/tile/{z}/{y}/{x} ; default

[ESRI_WorldTopo]
; Street Map 3D shaped
; ESRI/ARCGIS WorldTopo (see terms of use before using it)
Name=ESRI/ARCGIS WorldTopo
Enabled=false
;Http=https://services.arcgisonline.com/arcgis/rest/services/World_Topo_Map/MapServer/tile/{z}/{y}/{x} ; default

; ****
; USER Maps (your at your own here...)
; ****

[USER_TILES_1]
; User defines Tile Server No 1
Name=User Tiles 1
Enabled=false
;Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat ; MUST be changed to something meaningful

[USER_TILES_2]
; User defines Tile Server No 2
Name=User Tiles 2
Enabled=false
;Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat ; MUST be changed to something meaningful

[USER_TILES_3]
; User defines Tile Server No 3
Name=User Tiles 3

```

Enabled=false
;Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat ; MUST be changed to something meaningful

[USER_TILES_4]
; User defines Tile Server No 4
Name=User Tiles 4
Enabled=false
;Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat ; MUST be changed to something meaningful

[USER_TILES_5]
; User defines Tile Server No 5
Name=User Tiles 5
Enabled=false
;Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat ; MUST be changed to something meaningful

[USER_TILES_6]
; User defines Tile Server No 6
Name=User Tiles 6
Enabled=false
;Http=https://ip_or_address/route/{z}/{x}/{y}.imageformat ; MUST be changed to something meaningful