# Open Watcom C/C++ Programmer's Guide



Version 2.0



#### Notice of Copyright

Copyright © 2002-2021 the Open Watcom Contributors. Portions Copyright © 1984-2002 Sybase, Inc. and its subsidiaries. All rights reserved.

Any part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of anyone.

For more information please visit http://www.openwatcom.org/

Portions of this manual are reprinted with permission from Tenberry Software, Inc.

#### **Preface**

The *Open Watcom C/C++ Programmer's Guide* includes the following major components:

- DOS Programming Guide
- The DOS/4GW DOS Extender
- Windows 3.x Programming Guide
- Windows NT Programming Guide
- OS/2 Programming Guide
- Novell NLM Programming Guide
- Mixed Language Programming
- Common Problems

#### Acknowledgements

This book was produced with the Open Watcom GML electronic publishing system, a software tool developed by WATCOM. In this system, writers use an ASCII text editor to create source files containing text annotated with tags. These tags label the structural elements of the document, such as chapters, sections, paragraphs, and lists. The Open Watcom GML software, which runs on a variety of operating systems, interprets the tags to format the text into a form such as you see here. Writers can produce output for a variety of printers, including laser printers, using separately specified layout directives for such things as font selection, column width and height, number of columns, etc. The result is type-set quality copy containing integrated text and graphics.

Many users have provided valuable feedback on earlier versions of the Open Watcom C/C++ compilers and related tools. Their comments were greatly appreciated. If you find problems in the documentation or have some good suggestions, we would like to hear from you.

July, 1997.

#### Trademarks Used in this Manual

DOS/4G and DOS/16M are trademarks of Tenberry Software, Inc.

OS/2 is a trademark of International Business Machines Corp. IBM Developer's Toolkit, Presentation Manager, and OS/2 are trademarks of International Business Machines Corp. IBM is a registered trademark of International Business Machines Corp.

Intel and Pentium are registered trademarks of Intel Corp.

Microsoft, Windows and Windows 95 are registered trademarks of Microsoft Corp. Windows NT is a trademark of Microsoft Corp.

NetWare, NetWare 386, and Novell are registered trademarks of Novell, Inc.

Phar Lap, 286|DOS-Extender and 386|DOS-Extender are trademarks of Phar Lap Software, Inc.

UNIX is a registered trademark of The Open Group.

WATCOM is a trademark of Sybase, Inc. and its subsidiaries.

1 Open watcom C/C++ Application Development	
OOS Programming Guide	•••••
2 Creating 16-bit DOS Applications	
2.1 The Sample Application	
2.2 Building and Running the Sample DOS Application	
2.3 Debugging the Sample DOS Application	
3 Creating 32-bit Phar Lap 386 DOS-Extender Applications	
3.1 The Sample Application	
3.2 Building and Running the Sample 386 DOS-Extender Application	
3.3 Debugging the Sample 386 DOS-Extender Application	
4 Creating 32-bit DOS/4GW Applications	
4.1 The Sample Application	
4.2 Building and Running the Sample DOS/4GW Application	
4.3 Debugging the Sample DOS/4GW Application	
5 32-bit Extended DOS Application Development	
5.1 Introduction	
5.2 How can I write directly to video memory using a DOS extender?	
5.2.1 Writing to Video Memory under Tenberry Software DOS/4GW	
5.2.2 Writing to Video Memory under the Phar Lap 386 DOS-Extender	
5.3 How do I get information about free memory in the 32-bit environment?	
5.3.1 Getting Free Memory Information under DOS/4GW	
5.3.2 Getting Free Memory Information under the Phar Lap 386 DOS-Extender	
5.3.3 Getting Free Memory Information in the 32-bit Environment under Windows 3.x	
5.4 How do I access the first megabyte in the extended DOS environment?	
5.4.1 Accessing the First Megabyte under Tenberry Software DOS/4GW	
5.4.2 Accessing the First Megabyte under the Phar Lap 386 DOS-Extender	
5.5 How do I spawn a protected-mode application?	
5.5.1 Spawning Protected-Mode Applications Under Tenberry Software DOS/4GW	
5.5.2 Spawning Protected-Mode Applications Under Phar Lap 386 DOS-Extender	
5.6 How Can I Use the Mouse Interrupt (0x33) with DOS/4GW?	
5.7 How Do I Simulate a Real-Mode Interrupt with DOS/4GW?	
5.8 How do you install a bi-modal interrupt handler using DOS/4GW?	
he DOS/4GW DOS Extender	
6 The Tenberry Software DOS/4GW DOS Extender	,
7 Linear Executables	
7.1 The Linear Executable Format	
7.1.1 The Stub Program	
7.2 Memory Use	
8 Configuring DOS/4GW	
8.1 The DOS4G Environment Variable	
8.2 Changing the Switch Mode Setting	

	8.3 Fine Control of Memory Usage
	8.3.1 Specifying a Range of Extended Memory
	8.3.2 Using Extra Memory
	8.4 Setting Runtime Options
	8.5 Controlling Address Line 20
, ,	VMM
,	9.1 VMM Default Parameters
	9.2 Changing the Defaults
	9.2.1 The .VMC File
	7.2.1 THE VIVIC THE
10	Interrupt 21H Functions
	10.1 Functions 25H and 35H: Interrupt Handling in Protected Mode
	10.1.1 32-Bit Gates
	10.1.2 Chaining 16-bit and 32-bit Handlers
	10.1.3 Getting the Address of the Interrupt Handler
1 1	Later of 21H DDM F and an
ιI	Interrupt 31H DPMI Functions
	11.2 Int31H Function Calls
	11.2.1 Local Descriptor Table (LDT) Management Services
	11.2.1 Local Descriptor Table (LDT) Management Services
	11.2.3 Interrupt Services
	11.2.4 Translation Services
	11.2.5 DPMI Version
	11.2.6 Memory Management Services
	11.2.7 Page Locking Services
	11.2.8 Demand Paging Performance Tuning Services
	11.2.9 Physical Address Mapping
	11.2.10 Virtual Interrupt State Functions
	11.2.11 Vendor Specific Extensions
	11.2.12 Coprocessor Status
	11.2.12 Coprocessor Guidas
12	Utilities
	12.1 DOS4GW
	12.2 PMINFO
	12.3 PRIVATXM
	12.4 RMINFO
13	Error Messages
IJ	13.1 Kernel Error Messages
	13.2 DOS/4G Errors
	13.2 DOG/TO LITUIS
14	DOS/4GW Commonly Asked Questions
	14.1 Access to Technical Support
	14.2 Differences Within the DOS/4G Product Line
	14.3 Addressing
	14.4 Interrupt and Exception Handling
	14.5 Memory Management
	14.6 DOS, BIOS, and Mouse Services
	14.7 Virtual Memory
	14.8 Debugging

	14.9 Compatibility
Wi	ndows 3.x Programming Guide
	15 Creating 16-bit Windows 3.x Applications
	15.1 The Sample GUI Application
	15.2 Building and Running the GUI Application
	15.3 Debugging the GUI Application
	16 Porting Non-GUI Applications to 16-bit Windows 3.x
	16.1 Console Device in a Windowed Environment
	16.2 The Sample Non-GUI Application
	16.3 Building and Running the Non-GUI Application
	16.4 Debugging the Non-GUI Application
	16.5 Default Windowing Library Functions
	17 Creating 32-bit Windows 3.x Applications
	17.1 The Sample GUI Application
	17.2 Building and Running the GUI Application
	17.3 Debugging the GUI Application
	10 Dentine New CVII Applications to 22 kit Windows 2
	18 Porting Non-GUI Applications to 32-bit Windows 3.x
	18.2 The Sample Non-GUI Application
	18.3 Building and Running the Non-GUI Application
	18.4 Debugging the Non-GUI Application
	18.5 Default Windowing Library Functions
	19 The Open Watcom 32-bit Windows 3.x Extender
	19.1 Pointers
	19.2 Implementation Overview
	19.3 System Structure
	19.4 System Overview
	19.5 Steps to Obtaining a 32-bit Application
	20 Windows 3.x 32-bit Programming Overview
	20.1 WINDOWS.H
	20.2 Environment Notes
	20.3 Floating-point Emulation
	20.4 Multiple Instances
	20.5 Pointer Handling
	20.5.1 When To Convert Incoming Pointers
	20.5.2 When To Convert Outgoing Pointers
	20.5.2.1 SendMessage and SendDlgItemMessage
	20.5.3 GlobalAlloc and LocalAlloc
	20.5.4 Callback Function Pointers
	20.5.4.1 Window Sub-classing
	20.5.4.1 Wildow Sub-Classing  20.6 Calling 16-bit DLLs
	20.6.1 Making DLL Calls Transparent
	20.6.1 Making DLL Cans Transparent  20.7 Far Pointer Manipulation
	20.8 _16 Functions
	20.0 TO 1 UIICUOIIS

21 Windows 32-Bit Dynamic Link Libraries	
21.1 Introduction to 32-Bit DLLs	157
21.2 A Sample 32-bit DLL	158
21.3 Calling Functions in a 32-bit DLL from a 16-bit Application	160
21.4 Writing a 16-bit Cover for the 32-bit DLL	161
21.5 Creating and Debugging Dynamic Link Libraries	162
21.5.1 Building the Applications	163
21.5.2 Installing the Examples under Windows	163
21.5.3 Running the Examples	163
21.5.4 Debugging a 32-bit DLL	163
21.5.5 Summary	164
22 Interfacing Visual Basic and Open Watcom C/C++ DLLs	
22.1 Introduction to Visual Basic and DLLs	
22.2 A Working Example	
22.3 Sample Visual Basic DLL Programs	
22.3.1 Source Code for VBDLL32.DLL	
22.3.2 Source code for COVER16.DLL	
22.4 Compiling and Linking the Examples	170
23 WIN386 Library Functions and Macros	171
AllocAlias16	
AllocHugeAlias16	
_Call16	
DefineDLLEntry	
DefineUserProc16	
FreeAlias16	
FreeHugeAlias16	
FreeIndirectFunctionHandle	
GetIndirectFunctionHandle	
GetProc16	
InvokeIndirectFunction	
MapAliasToFlat	
MK_FP16	
MK_FP32	
MK_LOCAL32	
PASS_WORD_AS_POINTER	
ReleaseProc16	
Releaser 10010	173
24 32-bit Extended Windows Application Development	
24.1 Can you call 16-bit code from a 32-bit code?	197
24.2 Can I WinExec another Windows application?	
24.3 How do I add my Windows resources?	
24.4 What size of function pointers passed to Windows?	198
24.5 Why are 32-bit callback routines FAR?	198
24.6 Why use the _16 API functions?	198
24.7 What about pointers in structures?	
24.8 When do I use MK_FP32?	
24.9 What is the difference between AllocAlias16 and MK_FP16?	
24.10 Tell Me More About Thunking and Aliases	
25 Special Variables for Windows Programming	201

26 Definitions of Windows Terms	203
27 Special Windows API Functions	205
Windows NT Programming Guide	209
28 Windows NT Programming Overview	211
28.1 Windows NT Programming Note	211
28.2 Windows NT Character-mode Versus GUI	211
29 Creating Windows NT GUI Applications	213
29.1 The Sample GUI Application	213
29.2 Building and Running the GUI Application	213
29.3 Debugging the GUI Application	214
30 Creating Windows NT Character-mode Applications	217
30.1 The Sample Character-mode Application	217
30.2 Building and Running the Character-mode Application	217
30.3 Debugging the Character-mode Application	218
31 Windows NT Multi-threaded Applications	221
31.1 Programming Considerations	221
31.2 Creating Threads	221
31.2.1 Creating a New Thread	222
31.2.2 Terminating the Current Thread	222
31.2.3 Getting the Current Thread Identifier	222
31.3 A Multi-threaded Example	223
32 Windows NT Dynamic Link Libraries	225
32.1 Creating Dynamic Link Libraries	225
32.2 Creating a Sample Dynamic Link Library	226
32.3 Using Dynamic Link Libraries	229
32.4 The Dynamic Link Library Data Area	231
33 Creating Windows NT POSIX Applications	233
OS/2 Programming Guide	237
34 Creating 16-bit OS/2 1.x Applications	239
34.1 The Sample Application	239
34.2 Building and Running the Sample OS/2 1.x Application	240
34.3 Debugging the Sample OS/2 1.x Application	240
35 Creating 32-bit OS/2 Applications	243
35.1 The Sample Application	243
35.2 Building and Running the Sample OS/2 Application	244
35.3 Debugging the Sample OS/2 Application	244
36 OS/2 2.x Multi-threaded Applications	247
36.1 Programming Considerations	247

36.2 Creating Threads	24
36.2.1 Creating a New Thread	24
36.2.2 Terminating the Current Thread	
36.2.3 Getting the Current Thread Identifier	
36.3 A Multi-threaded Example	
36.4 Thread Limits	
37 OS/2 2.x Dynamic Link Libraries	25
37.1 Creating Dynamic Link Libraries	
37.2 Creating a Sample Dynamic Link Library	
37.3 Using Dynamic Link Libraries	
37.4 The Dynamic Link Library Data Area	
37.5 Dynamic Link Library Initialization/Termination	
57.5 Dynamic Link Library mitianzation/ Termination	2.
38 Programming for OS/2 Presentation Manager	25
38.1 Porting Existing C/C++ Applications	
38.1.1 An Example	
38.2 Calling Presentation Manager API Functions	
56.2 Canning Presentation Ivianager AP1 Functions	
39 Developing an OS/2 Physical Device Driver	26
39 Developing an OS/2 Physical Device Driver	
Novell NLM Programming Guide	26
10 011 1 211 1 10g. unitaring 0 u.u.	
40 Creating NetWare 386 NLM Applications	26
Mixed Language Programming	26
41 Inter-Language calls: C and FORTRAN	27
41.1 Symbol Naming Convention	
41.2 Argument Passing Convention	
41.3 Memory Model Compatibility	
41.4 Linking Considerations	
41.5 Integer Type Compatibility	
41.6 How do I pass integers from C to a FORTRAN function?	
41.7 How do I pass integers from FORTRAN to a C function?	
41.8 How do I pass a string from a C function to FORTRAN?	2
41.9 How do I pass a string from FORTRAN to a C function?	2
41.10 How do I access a FORTRAN common block from within C?	2
41.11 How do I call a C function that accepts a variable number of arguments?	
Common Problems	
42 Commonly Asked Questions and Answers	
42.1 Determining my current patch level	28
42.2 Converting to Open Watcom C/C++	28
42.2.1 Conversion from UNIX compilers	28
42.2.2 Conversion from IBM-compatible PC compilers	
42.3 What you should know about optimization	
42.4 The compiler cannot find "stdio.h"	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,

42.5 Resolving an "Undefined Reference" linker error	288
42.6 Why my variables are not set to zero	289
42.7 What does "size of DGROUP exceeds 64K" mean for 16-bit applications?	290
42.8 What does "NULL assignment detected" mean in 16-bit applications?	291
42.9 What "Stack Overflow!" means	292
42.10 Why redefinition errors are issued from WLINK	293
42.11 How more than 20 files at a time can be opened	294
42.12 How source files can be seen in the debugger	295
42.13 The difference between the "d1" and "d2" compiler options	

## List of Figures

Figure 1. Basic Memory Layout	4:
	4
Figure 3. Access Rights/Type	6.
Figure 4. Extended Access Rights/Type	60
Figure 5. WIN386 Structure	14
Figure 6, 32-bit Application Structure	

## 1 Open Watcom C/C++ Application Development

This document contains guides to application development for several environments including 16-bit DOS, 32-bit extended DOS, Windows 3.x, 32-bit extended Windows 3.x, Windows NT/2000/XP, Win9x, OS/2, and Novell NLMs. It also describes mixed language (C, FORTRAN) application development. It concludes with a chapter on some general questions and the answers to them.

This document covers the following topics:

• DOS Programming Guide

Creating 16-bit DOS Applications
Creating 32-bit Phar Lap 386|DOS-Extender Applications
Creating 32-bit DOS/4GW Applications
32-bit Extended DOS Application Development

The DOS/4GW DOS Extender

The Tenberry Software DOS/4GW DOS Extender
Linear Executables
Configuring DOS/4GW
VMM
Interrupt 21H Functions
Interrupt 31H DPMI Functions
Utilities
Error Messages
DOS/4GW Commonly Asked Questions

Windows 3.x Programming Guide

Creating 16-bit Windows 3.x Applications
Porting Non-GUI Applications to 16-bit Windows 3.x
Creating 32-bit Windows 3.x Applications
Porting Non-GUI Applications to 32-bit Windows 3.x
The Open Watcom 32-bit Windows Extender
Windows 3.x 32-bit Programming Overview
Windows 32-Bit Dynamic Link Libraries
Interfacing Visual Basic and Open Watcom C/C++ DLLs
WIN386 Library Functions and Macros
32-bit Extended Windows Application Development
Special Variables for Windows Programming
Definitions of Windows Terms
Special Windows API Functions

Windows NT Programming Guide

Windows NT Programming Overview Creating Windows NT GUI Applications Porting Non-GUI Applications to Windows NT GUI Windows NT Multi-threaded Applications Windows NT Dynamic Link Libraries

• OS/2 Programming Guide

Creating 16-bit OS/2 1.x Applications
Creating 32-bit OS/2 Applications
OS/2 Multi-threaded Applications
OS/2 Dynamic Link Libraries
Programming for OS/2 Presentation Manager

• Novell NLM Programming Guide

Creating NetWare 386 NLM Applications

• Mixed Language Programming

Inter-Language calls: C and FORTRAN

• Common Problems

Commonly Asked Questions and Answers

## **DOS Programming Guide**

## **2** Creating 16-bit DOS Applications

This chapter describes how to compile and link 16-bit DOS applications simply and quickly.

We will illustrate the steps to creating 16-bit DOS applications by taking a small sample application and showing you how to compile, link, run and debug it.

#### 2.1 The Sample Application

To demonstrate the creation of 16-bit DOS applications using command-line oriented tools, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
{
    printf( "Hello world\n" );
}
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
{
    cout << "Hello world" << endl;
}</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

#### 2.2 Building and Running the Sample DOS Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl -l=dos hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl -l=dos hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc hello.c
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 155, 0 warnings, 0 errors
Code size: 17
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a DOS executable
```

Provided that no errors were encountered during the compile or link phases, the "hello" program may now be run.

```
C>hello
Hello world
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). It is hello.exe that is run by DOS when you enter the "hello" command.

#### 2.3 Debugging the Sample DOS Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the *WCL* command, this is fairly straightforward. *WCL* recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl -l=dos -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl -l=dos -d2 hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc hello.c -d2
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 155, 0 warnings, 0 errors
Code size: 23
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a DOS executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. *WCL* will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, the following command may be issued.

C>wd hello

It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.



## 3 Creating 32-bit Phar Lap 386/DOS-Extender Applications

This chapter describes how to compile and link 32-bit Phar Lap 386 DOS-Extender applications simply and quickly.

We will illustrate the steps to creating 32-bit Phar Lap 386|DOS-Extender applications by taking a small sample application and showing you how to compile, link, run and debug it.

#### 3.1 The Sample Application

To demonstrate the creation of 32-bit Phar Lap 386|DOS-Extender applications using command-line oriented tools, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
{
    printf( "Hello world\n" );
}
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
{
    cout << "Hello world" << endl;
}</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

## 3.2 Building and Running the Sample 386/DOS-Extender Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl386 -l=pharlap hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=pharlap hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 24
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Phar Lap simple executable
```

Provided that no errors were encountered during the compile or link phases, the "hello" program may now be run.

```
C>run386 hello
Hello world
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exp (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). It is hello.exp that is run by DOS when you enter the "run386 hello" command.

#### 3.3 Debugging the Sample 386/DOS-Extender Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL386 command, this is fairly straightforward. WCL386 recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl386 -l=pharlap -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=pharlap -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 45
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Phar Lap simple executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. *WCL386* will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, the following command may be issued.

```
C>wd /trap=pls hello
```

It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.



## 4 Creating 32-bit DOS/4GW Applications

This chapter describes how to compile and link 32-bit DOS/4GW applications simply and quickly.

We will illustrate the steps to creating 32-bit DOS/4GW applications by taking a small sample application and showing you how to compile, link, run and debug it.

#### 4.1 The Sample Application

To demonstrate the creation of 32-bit DOS/4GW applications using command-line oriented tools, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
{
    printf( "Hello world\n" );
}
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
{
    cout << "Hello world" << endl;
}</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

#### 4.2 Building and Running the Sample DOS/4GW Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl386 -l=dos4g hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=dos4g hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 24
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a DOS/4G executable
```

Provided that no errors were encountered during the compile or link phases, the "hello" program may now be run.

```
C>hello
Hello world
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). It is hello.exe that is run by DOS when you enter the "hello" command.

#### 4.3 Debugging the Sample DOS/4GW Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the *WCL386* command, this is fairly straightforward. *WCL386* recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wc1386 -l=dos4g -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wc1386 -l=dos4q -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 45
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a DOS/4G executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. *WCL386* will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, the following command may be issued.

```
C>wd /trap=rsi hello
```

It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.

## 5 32-bit Extended DOS Application Development

#### 5.1 Introduction

The purpose of this chapter is to anticipate common programming questions for 32-bit extended DOS application development. Note that these programming solutions may be DOS-extender specific and therefore may not work for other DOS extenders.

The following topics are discussed in this chapter:

- How can I write directly to video memory using a DOS extender?
- How do I get information about free memory in the 32-bit environment?
- How do I access the first megabyte in the extended DOS environment?
- How do I spawn a protected-mode application?
- How can I use the mouse interrupt (0x33) with DOS/4GW?
- How do I simulate a real-mode interrupt with DOS/4GW?
- How do you install a bi-modal interrupt handler with DOS/4GW?

Please refer to the *DOS Protected-Mode Interface (DPMI) Specification* for information on DPMI services. In the past, the DPMI specification could be obtained free of charge by contacting Intel Literature JP26 at 800-548-4725 or by writing to the address below. We have been advised that the DPMI specification is no longer available in printed form.

Intel Literature JP26 3065 Bowers Avenue P.O. Box 58065 Santa Clara, California U.S.A. 95051-8065

However, the DPMI 1.0 specification can be obtained from the Intel ftp site. Here is the URL.

```
ftp://ftp.intel.com/pub/IAL/software_specs/dpmiv1.zip
```

This ZIP file contains a Postscript version of the DPMI 1.0 specification.

## 5.2 How can I write directly to video memory using a DOS extender?

Many programmers require access to video RAM in order to directly manipulate data on the screen. Under DOS, it was standard practice to use a far pointer, with the segment part of the far pointer set to the screen segment. Under DOS extenders, this practice is not so standard. Each DOS extender provides its own method for accessing video memory.

#### 5.2.1 Writing to Video Memory under Tenberry Software DOS/4GW

Under DOS/4GW, the first megabyte of physical memory is mapped as a shared linear address space. This allows your application to access video RAM using a near pointer set to the screen's linear address. The following program demonstrates this method.

```
/*
    SCREEN.C - This example shows how to write directly
    to screen memory under the DOS/4GW dos-extender.
    Compile & Link: wcl386 -1=dos4g SCREEN
#include <stdio.h>
#include <dos.h>
  Under DOS/4GW, the first megabyte of physical memory
  (real-mode memory) is mapped as a shared linear address
  space. This allows your application to access video RAM
  using its linear address. The DOS segment:offset of
  B800:0000 corresponds to a linear address of B8000.
 */
#define SCREEN_AREA 0xb800
#define SCREEN_LIN_ADDR ((SCREEN_AREA) << 4)</pre>
#define SCREEN SIZE 80*25
void main()
               *ptr;
    char
                i;
    /* Set the pointer to the screen's linear address */
    ptr = (char *)SCREEN_LIN_ADDR;
    for( i = 0; i < SCREEN_SIZE - 1; i++ ) {</pre>
        *ptr = '*';
        ptr += 2 * sizeof( char );
    }
}
```

Please refer to the chapter entitled "Linear Executables" on page 43 for more information on how DOS/4GW maps the first megabyte.

#### 5.2.2 Writing to Video Memory under the Phar Lap 386/DOS-Extender

The Phar Lap DOS extender provides screen access through the special segment selector 0x1C. This allows far pointer access to video RAM from a 32-bit program. The following example illustrates this technique.

```
SCREENPL.C - This example shows how to write directly
    to screen memory under the Phar Lap DOS extender.
    Compile & Link: wcl386 -l=pharlap SCREENPL
#include <stdio.h>
#include <dos.h>
    Phar Lap allows access to screen memory through a
    special selector. Refer to "Hardware Access" in
    Phar Lap's documentation for details.
#define PL_SCREEN_SELECTOR 0x1c
#define SCREEN_SIZE 80*25
void main()
    /* Need a far pointer to use the screen selector */
    char far *ptr;
    int
                i;
    /* Make a far pointer to screen memory */
    ptr = MK_FP( PL_SCREEN_SELECTOR, 0 );
    for( i = 0; i < SCREEN_SIZE - 1; i++ ) {
        *ptr = '*';
        ptr += 2 * sizeof( char );
    }
}
```

It is also possible to map screen memory into your near memory using Phar Lap system calls. Please refer to the chapter entitled "386|DOS-Extender System Calls" in Phar Lap's 386|DOS-Extender Reference Manual for details.

## 5.3 How do I get information about free memory in the 32-bit environment?

Under a virtual memory system, programmers are often interested in the amount of physical memory they can allocate. Information about the amount of free memory that is available is always provided under a DPMI host, however, the manner in which this information is provided may differ under various environments. Keep in mind that in a multi-tasking environment, the information returned to your task from the DPMI host can easily become obsolete if other tasks allocate memory independently of your task.

#### 5.3.1 Getting Free Memory Information under DOS/4GW

DOS/4GW provides a DPMI interface through interrupt 0x31. This allows you to use DPMI service 0x0500 to get free memory information. The following program illustrates this procedure.

```
MEMORY.C - This example shows how to get information
    about free memory using DPMI call 0500h under DOS/4GW.
    Note that only the first field of the structure is
    guaranteed to contain a valid value; any field that
    is not returned by DOS/4GW is set to -1 (OFFFFFFFFh).
    Compile & Link: wcl386 -l=dos4g memory
 */
#include <i86.h>
#include <dos.h>
#include <stdio.h>
#define DPMI_INT
                        0x31
struct meminfo {
   unsigned LargestBlockAvail;
   unsigned MaxUnlockedPage;
   unsigned LargestLockablePage;
    unsigned LinAddrSpace;
    unsigned NumFreePagesAvail;
    unsigned NumPhysicalPagesFree;
    unsigned TotalPhysicalPages;
    unsigned FreeLinAddrSpace;
    unsigned SizeOfPageFile;
    unsigned Reserved[3];
} MemInfo;
void main()
    union REGS regs;
    struct SREGS sregs;
    regs.x.eax = 0x00000500;
    memset( &sregs, 0, sizeof(sregs) );
    sregs.es = FP_SEG( &MemInfo );
    regs.x.edi = FP_OFF( &MemInfo );
```

```
int386x( DPMI_INT, &regs, &regs, &sregs );
   printf( "Largest available block (in bytes): %lu\n",
            MemInfo.LargestBlockAvail );
   printf( "Maximum unlocked page allocation: %lu\n",
           MemInfo.MaxUnlockedPage );
   printf( "Pages that can be allocated and locked: "
            "%lu\n", MemInfo.LargestLockablePage );
   printf( "Total linear address space including "
            "allocated pages: %lu\n",
           MemInfo.LinAddrSpace );
   printf( "Number of free pages available: %lu\n",
            MemInfo.NumFreePagesAvail );
   printf( "Number of physical pages not in use: %lu\n",
            MemInfo.NumPhysicalPagesFree );
   printf( "Total physical pages managed by host: %lu\n",
            MemInfo.TotalPhysicalPages );
   printf( "Free linear address space (pages): %lu\n",
            MemInfo.FreeLinAddrSpace );
   printf( "Size of paging/file partition (pages): %lu\n",
            MemInfo.SizeOfPageFile );
}
```

Please refer to the chapter entitled "Interrupt 31H DPMI Functions" on page 61 for more information on DPMI services.

#### 5.3.2 Getting Free Memory Information under the Phar Lap 386/DOS-Extender

Phar Lap provides memory statistics through 386|DOS-Extender System Call 0x2520. The following example illustrates how to use this system call from a 32-bit program.

```
MEMPLS40.C - This is an example of how to get the
    amount of physical memory present under Phar Lap
    386 DOS-Extender v4.0.
    Compile & Link: wcl386 -l=pharlap MEMPLS40
#include <dos.h>
#include <stdio.h>
typedef struct {
    unsigned data[25];
} pharlap_mem_status;
/* Names suggested in Phar Lap documentation */
#define APHYSPG
                    5
#define SYSPHYSPG
                    7
#define NFREEPG
                    21
unsigned long memavail (void)
    pharlap_mem_status status;
    union REGS regs;
    unsigned long amount;
```

Please refer to the chapter entitled "386|DOS-Extender System Calls" in Phar Lap's 386|DOS-Extender Reference Manual for more information on 386|DOS-Extender System Calls.

## 5.3.3 Getting Free Memory Information in the 32-bit Environment under Windows 3.x

Windows 3.x provides a DPMI host that you can access from a 32-bit program. The interface to this host is a 16-bit interface, hence there are some considerations involved when calling Windows 3.x DPMI services from 32-bit code. If a pointer to a data buffer is required to be passed in ES:DI, for example, an AllocAlias16() may be used to get a 16-bit far pointer that can be passed to Windows 3.x through these registers. Also, an int86() call should be issued rather than an int386() call. The following program demonstrates the techniques mentioned above.

```
/*
    MEMWIN.C - This example shows how to get information
    about free memory with DPMI call 0x0500 using Windows
    as a DPMI host. Note that only the first field of the
    structure is guaranteed to contain a valid value; any
    field that is not returned by the DPMI implementation
    is set to -1 (0FFFFFFFFh).

    Compile & Link: wcl386 -l=win386 -zw memwin
    Bind: wbind -n memwin
    */
#include <windows.h>
#include <i86.h>
#include <dos.h>
#include <stdio.h>
```

```
struct meminfo {
   unsigned LargestBlockAvail;
    unsigned MaxUnlockedPage;
    unsigned LargestLockablePage;
    unsigned LinAddrSpace;
    unsigned NumFreePagesAvail;
    unsigned NumPhysicalPagesFree;
    unsigned TotalPhysicalPages;
    unsigned FreeLinAddrSpace;
    unsigned SizeOfPageFile;
    unsigned Reserved[3];
} MemInfo;
#define DPMI_INT
                        0x31
void main()
    union REGS regs;
    struct SREGS sregs;
    DWORD mi_16;
    regs.w.ax = 0x0500;
    mi_16 = AllocAlias16( &MemInfo );
    sregs.es = HIWORD( mi_16 );
    regs.x.di = LOWORD( mi_16 );
    int86x( DPMI_INT, &regs, &regs, &sregs );
    printf( "Largest available block (in bytes): %lu\n",
            MemInfo.LargestBlockAvail );
    printf( "Maximum unlocked page allocation: %lu\n",
            MemInfo.MaxUnlockedPage );
    printf( "Pages that can be allocated and locked: "
            "%lu\n", MemInfo.LargestLockablePage );
    printf( "Total linear address space including "
            "allocated pages: %lu\n",
            MemInfo.LinAddrSpace );
    printf( "Number of free pages available: %lu\n",
             MemInfo.NumFreePagesAvail );
    printf( "Number of physical pages not in use: %lu\n",
             MemInfo.NumPhysicalPagesFree );
    printf( "Total physical pages managed by host: %lu\n",
             MemInfo.TotalPhysicalPages );
    printf( "Free linear address space (pages): %lu\n",
             MemInfo.FreeLinAddrSpace );
    printf( "Size of paging/file partition (pages): %lu\n",
             MemInfo.SizeOfPageFile );
    FreeAlias16( mi_16 );
}
```

Please refer to the *DOS Protected-Mode Interface (DPMI) Specification* for information on DPMI services. In the past, the DPMI specification could be obtained free of charge by contacting Intel Literature JP26 at 800-548-4725 or by writing to the address below. We have been advised that the DPMI specification is no longer available in printed form.

Intel Literature JP26 3065 Bowers Avenue P.O. Box 58065 Santa Clara, California U.S.A. 95051-8065 However, the DPMI 1.0 specification can be obtained from the Intel ftp site. Here is the URL.

```
ftp://ftp.intel.com/pub/IAL/software_specs/dpmiv1.zip
```

This ZIP file contains a Postscript version of the DPMI 1.0 specification.

## 5.4 How do I access the first megabyte in the extended DOS environment?

Many programmers require access to the first megabyte of memory in order to look at key low memory addresses. Under DOS, it was standard practice to use a far pointer, with the far pointer set to the segmented address of the memory area that was being inspected. Under DOS extenders, this practice is not so standard. Each DOS extender provides its own method for accessing the first megabyte of memory.

#### 5.4.1 Accessing the First Megabyte under Tenberry Software DOS/4GW

Under DOS/4GW, the first megabyte of physical memory - the real memory - is mapped as a shared linear address space. This allows your application to access the first megabyte of memory using a near pointer set to the linear address. The following program demonstrates this method. This example is similar to the screen memory access example.

```
KEYSTAT.C - This example shows how to get the keyboard
    status under DOS/4GW by looking at the ROM BIOS
    keyboard status byte in low memory.
    Compile & Link: wcl386 -l=dos4g keystat
#include <stdio.h>
#include <dos.h>
    Under DOS, the keyboard status byte has a segmented
    address of 0x0040:0x0017. This corresponds to a
    linear address of 0x417.
#define LOW_AREA 0x417
void main()
    /* Only need a near pointer in the flat model */
    char *ptr;
    /* Set pointer to linear address of the first
       status byte */
    ptr = (char *)LOW_AREA;
    /* Caps lock state is in bit 6 */
    if( *ptr & 0x40 ) {
        puts ( "Caps Lock on" );
    }
```

```
/* Num lock state is in bit 5 */
if( *ptr & 0x20 ) {
    puts( "Num Lock on" );
}
/* Scroll lock state is in bit 4 */
if( *ptr & 0x10 ) {
    puts( "Scroll Lock on" );
}
}
```

Please refer to the chapter entitled "Linear Executables" on page 43 for more information on how DOS/4GW maps the first megabyte.

### 5.4.2 Accessing the First Megabyte under the Phar Lap 386/DOS-Extender

The Phar Lap DOS extender provides access to real memory through the special segment selector 0x34. This allows far pointer access to the first megabyte from a 32-bit program. The following example illustrates this technique.

```
/*
    KEYSTAPL.C - This example shows how to get the keyboard
    status under 386 DOS-Extender by looking at the ROM
    BIOS keyboard status byte in low memory.
    Compile & Link: wcl386 -l=pharlap keystapl
 */
#include <stdio.h>
#include <dos.h>
    Under DOS, the keyboard status byte has a segmented
    address of 0x0040:0x0017. This corresponds to a
    linear address of 0x417.
void main()
    /* We require a far pointer to use selector
       for 1st megabyte */
    char far *ptr;
    /\star Set pointer to segmented address of the first
       status byte */
    ptr = MK_FP(0x34, 0x417);
    /* Caps lock state is in bit 6 */
    if( *ptr & 0x40 ) {
        puts ( "Caps Lock on" );
    /* Num lock state is in bit 5 */
    if( *ptr & 0x20 ) {
       puts( "Num Lock on" );
    /* Scroll lock state is in bit 4 */
    if( *ptr & 0x10 ) {
       puts( "Scroll Lock on" );
}
```

Please refer to the chapter entitled "Program Environment" in Phar Lap's 386|DOS-Extender Reference Manual for more information on segment selectors available to your program.

### 5.5 How do I spawn a protected-mode application?

Sometimes applications need to spawn other programs as part of their execution. In the extended DOS environment, spawning tasks is much the same as under DOS, however it should be noted that the only mode supported is P\_WAIT. The P\_OVERLAY mode is not supported since the DOS extender cannot be removed from memory by the application (this is also the reason why the exec() functions are unsupported). The other modes are for concurrent operating systems only.

Also, unless the application being spawned is bound or stubbed, the DOS extender must be spawned with the application and its arguments passed in the parameter list.

# 5.5.1 Spawning Protected-Mode Applications Under Tenberry Software DOS/4GW

In the case of DOS/4GW, some real-mode memory must be set aside at run time for spawning the DOS extender, otherwise the spawning application could potentially allocate all of system memory. The real memory can be reserved from within your program by assigning the global variable \_\_minreal the number of bytes to be set aside. This variable is referenced in <stdlib.h>. The following two programs demonstrate how to spawn a DOS/4GW application.

```
SPWNRD4G.C - The following program demonstrates how to
    spawn another DOS/4GW application.
    Compile and link: wcl386 -l=dos4g spwnrd4g
 */
#include <process.h>
#include <stdio.h>
#include <stdlib.h>
/* DOS/4GW var for WLINK MINREAL option */
unsigned __near __minreal = 100*1024;
void main()
    int app2_exit_code;
    puts ( "Spawning a protected-mode application..."
          "using spawnlp() with P_WAIT" );
    app2_exit_code = spawnlp( P_WAIT, "dos4gw",
                             "dos4gw", "spwndd4g", NULL );
    printf( "Application #2 returned with exit code %d\n",
                             app2_exit_code );
}
```

```
/*
    SPWNDD4G.C - Will be spawned by the SPWNRD4G program.

Compile & Link: wcl386 -l=dos4g spwndd4g
*/
#include <stdio.h>
#include <stdlib.h>

void main()
{
    puts( "\nApplication #2 spawned\n" );
    /* Send back exit code 59 */
    exit( 59 );
}
```

# 5.5.2 Spawning Protected-Mode Applications Under Phar Lap 386/DOS-Extender

In the case of the Phar Lap 386|DOS-Extender, some real-mode memory must be set aside at link time for spawning the DOS extender, otherwise the spawning application will be assigned all the system memory at startup. This is done at link time by specifying the **runtime minreal** and **runtime maxreal** options, as demonstrated by the following programs.

```
SPWNRPLS.C - The following program demonstrates how to
    spawn a Phar Lap application.
    Compile & Link:
    wcl386 -l=pharlap -"runt minr=300K, maxr=400K" spwnrpls
#include cess.h>
#include <stdio.h>
void main()
    int app2_exit_code;
    puts ( "Spawning a protect-mode application..."
          "using spawnlp() with P_WAIT" );
    puts( "Spawning application #2..." );
    app2_exit_code = spawnlp( P_WAIT, "run386",
                             "run386", "spwndpls", NULL );
    printf( "Application #2 returned with exit code %d",
                app2_exit_code );
}
```

```
/*
    SPWNDPLS.C - Will be spawned by the SPWNRPLS program.
    Compile & Link: wcl386 -l=pharlap spwndpls
    */
#include <stdio.h>
#include <stdlib.h>

void main()
{
    puts( "\nApplication #2 spawned\n" );
    /* Exit with error code 59 */
    exit( 59 );
}
```

### 5.6 How Can I Use the Mouse Interrupt (0x33) with DOS/4GW?

Several commonly used interrupts are automatically supported in protected mode with DOS/4GW. The DOS extender handles the switch from protected mode to real mode and manages any intermediate real-mode data buffers that are required. To use a supported interrupt, set up the register information as required for the interrupt and use one of the int386() or int386x() library functions to execute the interrupt. For calls that are not supported by DOS/4GW, you can use the DPMI function, Simulate a Real-Mode Interrupt (0x0300). This process is described in the next section.

Since the mouse interrupt (0x33) is quite commonly used, DOS/4GW provides protected-mode support for the interrupt and any mouse data buffer that is required. The following example demonstrates how a programmer could use the Microsoft standard mouse interrupt (0x33) from within a DOS/4GW application.

```
mouse.c - The following program demonstrates how
       to use the mouse interrupt (0x33) with DOS/4GW.
       Compile and link: wcl386 -1=dos4g mouse
#include <stdio.h>
#include <dos.h>
#include <i86.h>
/* Data touched at mouse callback time -- they are
  in a structure to simplify calculating the size
  of the region to lock.
struct callback_data {
   int
                  right_button;
    int
                   mouse event;
   unsigned short mouse_code;
   unsigned short mouse_bx;
   unsigned short mouse_cx;
   unsigned short mouse_dx;
   signed short mouse si;
    signed short mouse_di;
b = \{ 0 \};
```

```
/* Set up data buffer for mouse cursor bitmap */
unsigned short cursor[] = {
     /* 16 words of screen mask */
     0x3fff, /*0011111111111111*/
     0x1fff, /*000111111111111111/
0x0fff, /*00001111111111111/*/
     0x07ff, /*00000111111111111*/
     0x03ff, /*000000111111111111/
0x01ff, /*00000011111111111/
0x00ff, /*00000001111111111/
0x00ff, /*00000001111111111/
     0x007f, /*0000000011111111*/
     0x01ff, /*00000011111111111*/
0x10ff, /*00010000111111111*/
     0xb0ff, /*10110000111111111*/
     0xf87f, /*11111000011111111*/

0xf87f, /*1111100001111111*/

0xf83f, /*1111100001111111*/
     0xfc3f, /*11111100001111111*/
     0xfe1f, /*111111110000111111*/
     /* 16 words of cursor mask */
     0x0000, /*000000000000000*/
0x4000, /*010000000000000*/
     0x6000, /*0110000000000000*/
     0x7000, /*011100000000000000/
0x7800, /*01111000000000000/
0x7c00, /*0111110000000000/
0x7c00, /*0111110000000000/
     0x7e00, /*0111111000000000*/
     0x7f00, /*0111111100000000*/
0x7c00, /*0111111000000000*/
     0x4600, /*0100011000000000*/
     0x0600, /*0000011000000000*/
0x0300, /*000001100000000*/
     0x0300, /*000001100000000*/
     0x0180, /*000000110000000*/
     0x0180, /*000000110000000*/
0x00c0, /*000000011000000*/
int lock_region( void *address, unsigned length )
     union REGS
                          regs;
     unsigned
                          linear;
     /* Thanks to DOS/4GW's zero-based flat memory
         model, converting a pointer of any type to
         a linear address is trivial.
     linear = (unsigned)address;
     /* DPMI Lock Linear Region */
     regs.w.ax = 0x600;
     /* Linear address in BX:CX */
     regs.w.bx = (unsigned short)(linear >> 16);
     regs.w.cx = (unsigned short)(linear & 0xFFFF);
     /* Length in SI:DI */
     regs.w.si = (unsigned short)(length >> 16);
     regs.w.di = (unsigned short) (length & 0xFFFF);
     int386( 0x31, &regs, &regs );
     /* Return 0 if lock failed */
     return( !regs.w.cflag );
```

```
#pragma off( check_stack )
void _loadds far click_handler( int max, int mbx,
                                  int mcx, int mdx,
                                 int msi, int mdi )
#pragma aux click_handler __parm [EAX] [EBX] [ECX] \
                                  [EDX] [ESI] [EDI]
    cbd.mouse_event = 1;
    cbd.mouse_code = (unsigned short)max;
    cbd.mouse_bx = (unsigned short)mbx;
    cbd.mouse_cx = (unsigned short)mcx;
cbd.mouse_dx = (unsigned short)mdx;
    cbd.mouse_si = (signed short)msi;
cbd.mouse_di = (signed short)mdi;
    if(cbd.mouse_code & 8)
        cbd.right_button = 1;
/\star Dummy function so we can calculate size of
 code to lock (cbc_end - click_handler).
void cbc_end( void )
#pragma on( check_stack )
void main (void)
    struct SREGS sregs;
    union REGS
                        inregs, outregs;
    int
                        installed = 0;
    unsigned char
                         orig_mode = 0;
    unsigned short far *ptr;
    void (far *function_ptr)();
    segread( &sregs );
    /* get original video mode */
    inregs.w.ax = 0x0f00;
    int386( 0x10, &inregs, &outregs );
    orig_mode = outregs.h.al;
    /* goto graphics mode */
    inregs.h.ah = 0x00;
    inregs.h.al = 0x6;
    int386( 0x10, &inregs, &outregs );
    printf( "Previous Mode = u\n", orig_mode );
    printf( "Current Mode = u\n", inregs.h.al );
    /* check for mouse driver */
    inregs.w.ax = 0;
    int386( 0x33, &inregs, &outregs);
    if( installed = (outregs.w.ax == 0xffff) )
        printf( "Mouse installed...\n" );
        printf( "Mouse NOT installed...\n" );
```

*30* 

```
if( installed ) {
    /* lock callback code and data (essential under VMM!)
       note that click_handler, although it does a far
       return and is installed using a full 48-bit pointer,
       is really linked into the flat model code segment
       -- so we can use a regular (near) pointer in the
      lock_region() call.
    * /
    if( (! lock_region( &cbd, sizeof( cbd ) )) | |
        (! lock_region( (void near *)click_handler,
           (char *)cbc_end - (char near *)click_handler )) )
        printf( "locks failed\n" );
    } else {
        /* show mouse cursor */
        inregs.w.ax = 0x1;
        int386( 0x33, &inregs, &outregs);
        /* set mouse cursor form */
        inregs.w.ax = 0x9;
        inregs.w.bx = 0x0;
        inregs.w.cx = 0x0;
                    = cursor;
        inregs.x.edx = FP_OFF( ptr );
        sregs.es = FP_SEG( ptr );
        int386x( 0x33, &inregs, &outregs, &sregs );
        /* install click watcher */
        inregs.w.ax = 0xC;
        inregs.w.cx = 0x0002 + 0x0008;
        function_ptr = ( void (far *)( void ) )click_handler;
        inregs.x.edx = FP_OFF( function_ptr );
        sregs.es = FP_SEG( function_ptr );
        int386x( 0x33, &inregs, &outregs, &sregs );
        while( !cbd.right_button ) {
            if( cbd.mouse_event ) {
                printf( "Ev %04hxh BX %hu CX %hu DX %hu "
                        "SI %hd DI %hd\n",
                        cbd.mouse_code, cbd.mouse_bx,
                        cbd.mouse_cx, cbd.mouse_dx,
                        cbd.mouse_si, cbd.mouse_di );
                cbd.mouse_event = 0;
            }
       }
   }
/* check installation again (to clear watcher) */
inregs.w.ax = 0;
int386( 0x33, &inregs, &outregs );
if ( outregs.w.ax == 0xffff )
   printf( "DONE : Mouse still installed...\n" );
else
    printf( "DONE : Mouse NOT installed...\n" );
printf( "Press Enter key to return to original mode \n" );
getc( stdin );
inregs.h.ah = 0x00;
inregs.h.al = orig_mode;
int386( 0x10, &inregs, &outregs );
```

### 5.7 How Do I Simulate a Real-Mode Interrupt with DOS/4GW?

Some interrupts are not supported in protected mode with DOS/4GW but they can still be called using the DPMI function, Simulate Real-Mode Interrupt (0x0300). Information that needs to be passed down to the real-mode interrupt is transferred using an information data structure that is allocated in the protected-mode application. The address to this protected-mode structure is passed into DPMI function 0x0300. DOS/4GW will then use this information to set up the real-mode registers, switch to real mode and then execute the interrupt in real mode.

If your protected-mode application needs to pass data down into the real-mode interrupt, an intermediate real-mode buffer must be used. This buffer can be created using DPMI function 0x0100 to allocate real-mode memory. You can then transfer data from the protected-mode memory to the real-mode memory using a far pointer as illustrated in the "SIMULATE.C" example.

The following example illustrates how to allocate some real-mode memory, transfer a string of characters from protected mode into the real-mode buffer, then set up and call the Interrupt 0x0021 function to create a directory. The string of characters are used to provide the directory name. This example can be adapted to handle most real-mode interrupt calls that aren't supported in protected mode.

```
SIMULATE.C - Shows how to issue a real-mode interrupt
    from protected mode using DPMI call 300h. Any buffers
    to be passed to DOS must be allocated in DOS memory
    This can be done with DPMI call 100h. This program
    will call DOS int 21, function 39h, "Create
   Directory".
    Compile & Link: wcl386 -l=dos4g simulate
#include <i86.h>
#include <dos.h>
#include <stdio.h>
#include <string.h>
static struct rminfo {
    long EDI;
    long ESI;
    long EBP:
    long reserved_by_system;
    long EBX;
    long EDX;
    long ECX;
    long EAX;
    short flags;
    short ES, DS, FS, GS, IP, CS, SP, SS;
} RMI;
void main()
    union REGS regs;
    struct SREGS sreas:
    int interrupt_no=0x31;
    short selector;
    short segment;
    char far *str;
    /* DPMI call 100h allocates DOS memory */
   memset(&sregs, 0, sizeof(sregs));
    regs.w.ax=0x0100;
    regs.w.bx=0x0001;
    int386x( interrupt_no, &regs, &regs, &sregs);
    segment=regs.w.ax;
    selector=regs.w.dx;
```

```
/* Move string to DOS real-mode memory */
str=MK_FP(selector,0);
_fstrcpy( str, "myjunk" );

/* Set up real-mode call structure */
memset(&RMI,0,sizeof(RMI));
RMI.EAX=0x00003900; /* call service 39h ah=0x39 */
RMI.DS=segment; /* put DOS seg:off into DS:DX*/
RMI.EDX=0; /* DOS ignores EDX high word */
/* Use DPMI call 300h to issue the DOS interrupt */
regs.w.ax = 0x0300;
regs.h.bl = 0x21;
regs.h.bh = 0;
regs.w.cx = 0;
sregs.es = FP_SEG(&RMI);
regs.x.edi = FP_OFF(&RMI);
int386x( interrupt_no, &regs, &regs, &sregs );
}
```

# 5.8 How do you install a bi-modal interrupt handler using DOS/4GW?

Due to the nature of the protected-mode/real-mode interface, it is often difficult to handle high speed communications with hardware interrupt handlers. For example, if you install your communications interrupt handler in protected mode, you may find that some data is lost when transmitting data from a remote machine at the rate of 9600 baud. This occurs because the data arrived at the communication port while the machine was in the process of transferring the previous interrupt up to protected mode. Data will also be lost if you install the interrupt handler in real mode since your program, running in protected mode, will have to switch down into real mode to handle the interrupt. The reason for this is that the data arrived at the communication port while the DOS extender was switching between real mode and protected mode, and the machine was not available to process the interrupt.

To avoid the delay caused by switching between real-mode and protected mode to handle hardware interrupts, install interrupt handlers in both real-mode and protected-mode. During the execution of a protected-mode program, the system often switches down into real-mode for DOS system calls. If a communications interrupt occurs while the machine is in real-mode, then the real-mode interrupt handler will be used. If the interrupt occurs when the machine is executing in protected-mode, then the protected-mode interrupt handler will be used. This enables the machine to process the hardware interrupts faster and avoid the loss of data caused by context switching.

Installing the interrupt handlers in both protected-mode and real-mode is called bi-modal interrupt handling. The following program is an example of how to install both handlers for Interrupt 0x0C (also known as COM1 or IRQ4). The program writes either a 'P' to absolute address 0xB8002 or an 'R' to absolute address 0xB8000. These locations are the first two character positions in screen memory for a color display. As the program runs, you can determine which interrupt is handling the COM1 port by the letter that is displayed. A mouse attached to COM1 makes a suitable demo. Type on the keyboard as you move the mouse around. The ESC key can be used to terminate the program. Transmitted data from a remote machine at 9600 baud can also be used to test the COM1 handling.

```
BIMODAL.C - The following program demonstrates how
    to set up a bi-modal interrupt handler for DOS/4GW
    Compile and link: wcl386 -l=dos4g bimodal bimo.obj
#include <stdio.h>
#include <comio.h>
#include <dos.h>
#define D32RealSeg(P)
                        ((((DWORD) (P)) >> 4) \& 0xFFFF)
#define D32RealOff(P) (((DWORD) (P)) & 0xF)
typedef unsigned int WORD;
typedef unsigned long DWORD;
extern void com1_init (void);
extern void __interrupt pmhandler (void);
extern void __interrupt __far rmhandler (void);
void *D32DosMemAlloc (DWORD size)
   union REGS r;
                               /* DPMI allocate DOS memory */
   r.x.eax = 0x0100;
    r.x.ebx = (size + 15) >> 4; /* Number of paragraphs requested */
    int386 (0x31, &r, &r);
    if( r.x.cflag ) /* Failed */
       return ((DWORD) 0);
    return (void *) ((r.x.eax & 0xFFFF) << 4);
void main (void)
                 r;
   union REGS
    struct SREGS
                  *lowp;
                  *fh;
    void far
    WORD
                   orig_pm_sel;
   DWORD
                  orig_pm_off;
    WORD
                  orig_rm_seg;
    WORD
                   orig_rm_off;
    int
/* Save the starting protected-mode handler address */
    r.x.eax = 0x350C; /* DOS get vector (INT 0Ch) */
    sr.ds = sr.es = 0;
    int386x (0x21, &r, &r, &sr);
    orig_pm_sel = (WORD) sr.es;
   orig_pm_off = r.x.ebx;
    Save the starting real-mode handler address using DPMI
    (INT 31h).
    r.x.eax = 0x0200; /* DPMI get real mode vector */
    r.h.bl = 0x0C;
    int386 (0x31, &r, &r);
    orig_rm_seg = (WORD) r.x.ecx;
    orig_rm_off = (WORD) r.x.edx;
    Allocate 128 bytes of DOS memory for the real-mode
    handler, which must of course be less than 128 bytes
    long. Then copy the real-mode handler into that
    segment.
    if(! ( lowp = D32DosMemAlloc(128) ) ) {
        printf ("Couldn't get low memory!\n");
        exit (1);
    memcpy (lowp, (void *) rmhandler, 128);
```

```
Install the new protected-mode vector. Because INT \mbox{OCh}
is in the auto-passup range, its normal "passdown"
behavior will change as soon as we install a
protected-mode handler. After this next call, when a
real mode INT OCh is generated, it will be resignalled
in protected mode and handled by pmhandler.
r.x.eax = 0x250C;
                   /* DOS set vector (INT 0Ch) */
fh = (void far *) pmhandler;
r.x.edx = FP_OFF (fh);
/* DS:EDX == &handler */
sr.ds = FP\_SEG (fh);
sr.es = 0;
int386x (0x21, &r, &r, &sr);
Install the new real-mode vector. We do this after
installing the protected-mode vector in order to
override the "passup" behavior. After the next call,
interrupts will be directed to the appropriate handler,
regardless of which mode we are in when they are
generated.
r.x.eax = 0x0201;
r.h.bl = 0x0C;
/* CX:DX == real mode &handler */
r.x.ecx = D32RealSeg(lowp);
r.x.edx = D32RealOff(lowp);
int386 (0x31, &r, &r);
Initialize COM1.
com1_init ();
puts( "Move mouse, transmit data; ESC to quit\n" );
while(1){
    if( kbhit() ) {
       if( (c = getch ()) & 0xff) == 27)
               break;
        putch (c);
    }
delay(1);
}
Clean up.
r.x.eax = 0x250C; /* DOS set vector (INT 0Ch) */
r.x.edx = orig_pm_off;
sr.ds = orig_pm_sel;
                        /* DS:EDX == &handler */
sr.es = 0;
int386x (0x21, &r, &r, &sr);
r.x.eax = 0x0201; /* DPMI set real mode vector */
r.h.bl = 0x0C;
/* CX:DX == real mode &handler */
r.x.ecx = (DWORD) orig_rm_seg;
r.x.edx = (DWORD) orig_rm_off;
int386 (0x31, &r, &r);
```

You will also need to create the following assembler code module. The first part provides the interrupt handling routine for the real-mode interrupt handler. The second provides the protected-mode version of the interrupt handler.

```
; * *
;** bimo.asm:
; ** Assembler code for real-mode and protected-mode
;** INT 0xC interrupt handlers to support the INT 0xC
; ** interrupt in both modes
; * *
.386
; * *
;** The real-mode interrupt handler is in a 16-bit code
;** segment so that the assembler will generate the right
;** code. We will copy this code down to a 16-bit segment
;** in low memory rather than executing it in place.
_TEXT16 SEGMENT BYTE PUBLIC USE16 'CODE'
    ASSUME cs:_TEXT16
    PUBLIC rmhandler_
rmhandler_:
    push
    push
           bx
    mov
           bx,0B800h
                                   ; ES = 0xB800
           es,bx
    mov
           sub
    mov
           WORD PTR es: [bx+2], 0720h
    mov
           BYTE PTR es:[bx],'R'
                                  ; Write R to memory
    mov
    pop
           bx
            es
    pop
    push
           ax
    push
           dx
           dx,03FAh
    mov
    in
           al,dx
                                   ; Read ports so
    mov
           dx,03F8h
                                  ; interrupts can
          al,dx
dx,020h
    in
                                   ; continue to be
    mov
                                   ; generated
    mov
          al,dl
          dx,al
                                   ; Send EOI
    out
    pop
           dx
    pop
           ax
    iret
_TEXT16 ENDS
;** The protected-mode interrupt handler is in a 32-bit code
;** segment. Even so, we have to be sure to force an <code>IRETD</code>
;** at the end of the handler, because MASM doesn't generate
; ** one. This handler will be called on a 32-bit stack by
; ** DOS/4GW.
; ** _DATA is the flat model data segment, which we load into
;** ES so we can write to absolute address 0xB8000. (In the
;** flat model, DS is based at 0.)
; * *
_DATA
        SEGMENT BYTE PUBLIC USE32 'DATA'
_DATA
       ENDS
```

```
DGROUP GROUP _DATA
_TEXT SEGMENT BYTE PUBLIC USE32 'CODE'
   ASSUME cs:_TEXT
   PUBLIC com1_init_
com1_init_:
   mov
           ax,0F3h
                                 ; 9600,n,8,1
          dx, 0
                                 ; com1
; Initialize COM1
; COM1 port space
   mov
         un,
14h
   int
   mov
        bx,03F8h
          bx,03F8h
dx,[bx+5]
   lea
                                 ; line status reg
    in
           al,dx
           dx, [bx+4]
                                 ; modem control reg
   lea
           al,dx
    in
   or
           al,8
                                  ; enable OUT2 int
           dx,al
   out
           dx, [bx+2]
    lea
                                 ; int id register
           al,dx
    in
   mov
           dx,bx
                                  ; data receive reg
    in
           al,dx
           al,21h
                                 ; interrupt mask reg
    in
    and
           al,0EFh
                                  ; force IRQ4 unmask
           21h,al
   out
    lea
           dx, [bx+1]
                                 ; int enable reg
   mov
           al,1
                                  ; enable received int
   out
           dx,al
    ret
   PUBLIC pmhandler_
pmhandler_:
   push
   push
           bx
           bx,DGROUP
   mov
           es,bx
   mov
                         ; ES:EBX=flat:0B8000h
           ebx,0B8000h
   mov
           DWORD PTR es:[ebx],07200720h ; Clear cells
   mov
           BYTE PTR es: [ebx+2], 'P'; Write P to memory
   mov
   pop
   pop
           es
   push
           ax
   push
           dx
           dx,03FAh
   mov
    in
           al,dx
                                  ; Read ports so
           dx,03F8h
   mov
                                  ; interrupts can
           al,dx
                                  ; continue to be
           dx,020h
   mov
                                  ; generated
   mov
           al,dl
           dx,al
                                  ; Send EOI
   out
           dx
   pop
   pop
   iretd
_TEXT ENDS
   END
```

# The DOS/4GW DOS Extender

## 6 The Tenberry Software DOS/4GW DOS Extender

The chapters in this section describe the 32-bit Tenberry Software *DOS/4GW* DOS Extender which is provided with the Open Watcom C/C++ package. *DOS/4GW* is a subset of Tenberry Software's DOS/4G product. *DOS/4GW* is customized for use with the Open Watcom C/C++ package. Key differences are:

- *DOS/4GW* will only execute programs built with a Open Watcom 32-bit compiler such as Open Watcom C/C++ and linked with its run-time libraries.
- The *DOS/4GW* virtual memory manager (VMM), included in the package, is restricted to 32MB of memory.
- *DOS/4GW* does not provide extra functionality such as TSR capability and VMM performance tuning enhancements.

If your application has requirements beyond those provided by *DOS/4GW*, you may wish to acquire DOS/4GW Professional or DOS/4G from:

```
Tenberry Software, Inc.
PO Box 20050
Fountain Hills, Arizona
U.S.A 85269-0050

WWW: http://www.tenberry.com/dos4g/
Email: info@tenberry.com
Phone: 1.480.767.8868
Fax: 1.480.767.8709
```

Programs developed to use the restricted version of *DOS/4GW* which is included in the Open Watcom C/C++ package can be distributed on a royalty-free basis, subject to the licensing terms of the product.

### 7 Linear Executables

To build a linear executable, compile and link it as described in the chapter entitled "Creating 32-bit DOS/4GW Executables". The resulting file will not run independently: you can run it under the Open Watcom Debugger, Tenberry Software Instant-D debugger, or with the standalone "DOS4GW.EXE".

### 7.1 The Linear Executable Format

DOS/4GW works with files that use the Linear Executable (LE) file format. The format represents a protected-mode program in the context of a 32-bit 386 runtime environment with linear to physical address translation hardware enabled. It uses a flat address space.

This file format is similar to the Segmented Executable (NE) format used in OS/2 1.x and MS Windows. Both support Dynamic Linking, Resources, and are geared toward protected-mode programs. Both formats use tables of "counted ASCII" names, and they use similar relocation formats.

Both formats begin with a DOS style stub program that sophisticated loaders skip. This stub program executes when the *DOS/4GW* loader is not present, displaying the message, *This program cannot run in DOS mode*.

When the Open Watcom Linker is used to link a *DOS/4GW* application, it automatically replaces the default stub program with one that calls DOS4GW.

### 7.1.1 The Stub Program

The stub at the beginning of a linear executable is a real-mode program that you can modify as you like. For example, you can:

- make the stub program do a checksum on the "DOS4GW.EXE" file to make sure it's the correct version.
- copy protect your program.
- specify a search path for the "DOS4GW.EXE" file.
- add command line arguments.

The SRC directory contains source code for a sample stub program. "WSTUB.C" is a simple example, a good base to start from when you construct your own stub. Please note that you will require a 16-bit C compiler to compile a new stub program. Following is the code in "WSTUB.C":

```
#include <stdio.h>
#include <stdlib.h>
#include cess.h>
#include <errno.h>
#include <string.h>
/* Add environment strings to be searched here */
char *paths_to_check[] = {
        "DOS4GPATH",
        "PATH" };
char *dos4g_path()
    static char fullpath[80];
    int i;
    for(i = 0;
         i < sizeof( paths_to_check ) / sizeof( paths_to_check[0] );</pre>
        _searchenv( "dos4gw.exe", paths_to_check[i], fullpath );
        if( fullpath[0] ) return( &fullpath );
    for( i = 0;
         i < sizeof( paths_to_check ) / sizeof( paths_to_check[0] );</pre>
         i++ ) {
         _searchenv( "dos4g.exe", paths_to_check[i], fullpath);
        if( fullpath[0] ) return( &fullpath );
    return( "dos4gw.exe");
main( int argc, char *argv[] )
    char *av[4];
   auto char cmdline[128];
   av[0] = dos4g_path();
                                        /* Locate the DOS/4G loader */
                                        /* name of executable to run */
    av[1] = argv[0];
    av[2] = getcmd( cmdline );
                                        /* command line */
    av[3] = NULL;
                                        /* end of list */
#ifdef QUIET
   putenv( "DOS4G=QUIET" );  /* disables DOS/4G Copyright banner */
#endif
    execvp( av[0], av );
   puts( "Stub exec failed:" );
   puts( av[0] );
   puts( strerror( errno ) );
                                /* indicate error */
   exit(1);
```

### 7.2 Memory Use

This section explains how a *DOS/4GW* application uses the memory on a 386-based PC/AT. The basic memory layout of an AT machine consists of 640KB of DOS memory, 384KB of upper memory, and an undetermined amount of extended memory. DOS memory and upper memory together compose real memory, the memory that can be addressed when the processor is running in real mode.



Figure 1. Basic Memory Layout

Under *DOS/4GW*, the first megabyte of physical memory — the real memory — is mapped as a shared linear address space. This allows your application to use absolute addresses in real memory, to access video RAM or BIOS ROM, for example. Because the real memory is available to all processes, you are not guaranteed to be able to allocate a particular area in real memory: another process may have allocated it already.

Most code and data is placed in a paged linear address space starting at 4MB. The linear address space starts at 4MB, the first address in the second page table, to avoid conflicts with VCPI system software.

This split mapping — an executable that is linked to start at 4MB in the linear address space, with the first MB in the address space mapped to the first MB of physical memory — is called a *split flat model*.

The illustration below shows the layout of physical memory on the left, and the layout of the linear address space on the right.



Figure 2. Physical Memory/Linear Address Space

The 1KB label in the diagram indicates the top of the real-mode interrupt vectors. 4KB marks the end of the first page.

# 8 Configuring DOS/4GW

This chapter explains various options that can be specified with the **DOS4G** environment variable including how to suppress the banner that is displayed by *DOS/4GW* at startup. It also explains how to use the **DOS16M** environment variable to select the switch mode setting, if necessary, and to specify the range of extended memory in which *DOS/4GW* will operate. *DOS/4GW* is based on Tenberry Software's DOS/16M 16-bit Protected-Mode support; hence the **DOS16M** environment variable name remains unchanged.

### 8.1 The DOS4G Environment Variable

A number of options can be selected by setting the **DOS4G** environment variable. The syntax for setting options is:

```
set DOS4G=option1, option2, ...
```

Do not insert a space between **DOS4G** and the equal sign. A space to the right of the equal sign is optional.

#### **Options:**

**QUIET** 

Use this option to suppress the *DOS/4GW* banner.

The banner that is displayed by *DOS/4GW* at startup can be suppressed by issuing the following command:

```
set DOS4G=quiet
```

**Note:** Use of the quiet switch is only permitted pursuant to the terms and conditions of the WATCOM Software License Agreement and the additional redistribution rights described in the *Getting Started* manual. Under these terms, suppression of the copyright by using the quiet switch is not permitted for applications which you distribute to others.

**VERBOSE** 

Use this option to maximize the information available for postmortem debugging.

Before running your application, issue the following command:

```
set DOS4G=verbose
```

Reproduce the crash and record the output.

**NULLP** 

Use this option to trap references to the first sixteen bytes of physical memory.

Before running your application, issue the following command:

```
set DOS4G=nullp
```

To select a combination of options, list them with commas as separators.

Example:

set DOS4G=nullp, verbose

### 8.2 Changing the Switch Mode Setting

In almost all cases, *DOS/4GW* programs can detect the type of machine that is running and automatically choose an appropriate real- to protected-mode switch technique. For the few cases in which this default setting does not work we provide the **DOS16M** DOS environment variable, which overrides the default setting.

Change the switch mode settings by issuing the following command:

set DOS16M=value

Do not insert a space between **DOS16M** and the equal sign. A space to the right of the equal sign is optional.

The table below lists the machines and the settings you would use with them. Many settings have mnemonics, listed in the column "Alternate Name", that you can use instead of the number. Settings that you must set with the **DOS16M** variable have the notation req'd in the first column. Settings you may use are marked *option*, and settings that will automatically be set are marked *auto*.

Status	Machine	Setting	Alternate Name	Comment
auto req'd auto auto auto req'd auto req'd req'd option	386/486 w/ DPMI NEC 98-series PS/2 386/486 386 Fujitsu FMR-70 386/486 w/ VCPI Hitachi B32 OKI if800 IBM PS/55	0 1 2 3 INBOARD 5 11 14 15	None 9801 None 386, 80386 None None None None None	Set automatically if DPMI is active Must be set for NEC 98-series Set automatically for PS/2 Set automatically for 386 or 486 386 with Intel Inboard Must be set for Fujitsu FMR-70 Set automatically if VCPI detected Must be set for Hitachi B32 Must be set for OKI if800 May be needed for some PS/55s

The following procedure shows you how to test the switch mode setting.

1. If you have one of the machines listed below, set the **DOS16M** environment variable to the value shown for that machine and specify a range of extended memory. For example, if your machine is a NEC 98-series, set DOS16M=1 @2M-4M. See the section entitled "Fine Control of Memory Usage" on page 49 in this chapter for more information about setting the memory range.

Machine	Setting
NEC 98-series	1
Fujitsu FMR-60,-70	5
Hitachi B32	14
OKI if800	15

Before running *DOS/4GW* applications, check the switch mode setting by following this procedure:

 Run PMINFO and note the switch setting reported on the last line of the display. (PMINFO, which reports on the protected-mode resources available to your programs, is described in more detail in the chapter entitled "Utilities" on page 87)

If PMINFO runs, the setting is usable on your machine.

3. If you changed the switch setting, add the new setting to your AUTOEXEC.BAT file.

**Note:** PMINFO will run successfully on 286 machines. If your *DOS/4GW* application does not run, and PMINFO does, check the CPU type reported on the first line of the display.

You are authorized (and encouraged) to distribute PMINFO to your customers. You may also include a copy of this section in your documentation.

### 8.3 Fine Control of Memory Usage

In addition to setting the switch mode as described above, the **DOS16M** environment variable enables you to specify which portion of extended memory *DOS/4GW* will use. The variable also allows you to instruct *DOS/4GW* to search for extra memory and use it if it is present.

#### 8.3.1 Specifying a Range of Extended Memory

Normally, you don't need to specify a range of memory with the **DOS16M** variable. You must use the variable, however, in the following cases:

- You are running on a Fujitsu FMR-series, NEC 98-series, OKI if800-series or Hitachi B-series machine.
- You have older programs that use extended memory but don't follow one of the standard disciplines.
- You want to shell out of *DOS/4GW* to use another program that requires extended memory.

If none of these conditions applies to you, you can skip this section.

The general syntax is:

```
set DOS16M= [switch_mode] [@start_address [- end_address]] [:size]
```

In the syntax shown above, start\_address, end\_address and size represent numbers, expressed in decimal or in hexadecimal (hex requires a 0x prefix). The number may end with a K to indicate an

address or size in kilobytes, or an M to indicate megabytes. If no suffix is given, the address or size is assumed to be in kilobytes. If both a size and a range are specified, the more restrictive interpretation is used.

The most flexible strategy is to specify only a size. However, if you are running with other software that does not follow a convention for indicating its use of extended memory, and these other programs start before *DOS/4GW*, you will need to calculate the range of memory used by the other programs and specify a range for *DOS/4GW* programs to use.

*DOS/4GW* ignores specifications (or parts of specifications) that conflict with other information about extended memory use. Below are some examples of memory usage control:

set DOS16M=1 @2m-4m Mode 1, for NEC 98-series machines, and use extended memory

between 2.0 and 4.0MB.

set DOS16M=:1M Use the last full megabyte of extended memory, or as much as

available limited to 1MB.

set DOS16M=@2m Use any extended memory available above 2MB.

set DOS16M= @ 0 - 5m Use any available extended memory from 0.0 (really 1.0) to

5.0MB.

set DOS16M=:0 Use no extended memory.

As a default condition *DOS/4GW* applications take all extended memory that is not otherwise in use. Multiple *DOS/4GW* programs that execute simultaneously will share the reserved range of extended memory. Any non-*DOS/4GW* programs started while *DOS/4GW* programs are executing will find that extended memory above the start of the *DOS/4GW* range is unavailable, so they may not be able to run. This is very safe. There will be a conflict only if the other program does not check the BIOS configuration call (Interrupt 15H function 88H, get extended memory size).

To create a private pool of extended memory for your *DOS/4GW* application, use the PRIVATXM program, described in the chapter entitled "Utilities" on page 87.

The default memory allocation strategy is to use extended memory if available, and overflow into DOS (low) memory.

In a VCPI or DPMI environment, the start\_address and end\_address arguments are not meaningful. *DOS/4GW* memory under these protocols is not allocated according to specific addresses because VCPI and DPMI automatically prevent address conflicts between extended memory programs. You can specify a size for memory managed by VCPI or DPMI, but *DOS/4GW* will not necessarily allocate this memory from the highest available extended memory address, as it does for memory managed under other protocols.

### 8.3.2 Using Extra Memory

Some machines contain extra non-extended, non-conventional memory just below 16MB. When *DOS/4GW* runs on a Compaq 386, it automatically uses this memory because the memory is allocated according to a certain protocol, which *DOS/4GW* follows. Other machines have no protocol for allocating this memory. To use the extra memory that may exist on these machines, set **DOS16M** with the + option.

set DOS16M=+

Setting the + option causes *DOS/4GW* to search for memory in the range from FA0000 to FFFFFF and determine whether the memory is usable. *DOS/4GW* does this by writing into the extra memory and reading what it has written. In some cases, this memory is mapped for DOS or BIOS usage, or for other system uses. If *DOS/4GW* finds extra memory that is mapped this way, and is not marked read-only, it will write into that memory. This will cause a crash, but won't have any other effect on your system.

### 8.4 Setting Runtime Options

The **DOS16M** environment variable sets certain runtime options for all *DOS/4GW* programs running on the same system.

To set the environment variable, the syntax is:

```
set DOS16M=[switch_mode_setting]^options.
```

**Note:** Some command line editing TSRs, such as CED, use the caret (^) as a delimiter. If you want to set **DOS16M** using the syntax above while one of these TSRs is resident, modify the TSR to use a different delimiter.

These are the options:

check A20 line -- This option forces DOS/4GW to wait until the A20 line is enabled before switching to protected mode. When DOS/4GW switches to real mode, this option suspends your program's execution until the A20 line is disabled, unless an XMS manager (such as HIMEM.SYS) is active. If an XMS manager is running, your program's execution is suspended until the A20 line is restored to the state it had when the CPU was last in real mode. Specify this option if you have a machine that runs DOS/4GW but is not truly AT-compatible. For more information on the A20 line, see the section entitled "Controlling Address Line 20" on page 52.

0x02

prevent initialization of VCPI -- By default, DOS/4GW searches for a VCPI server and, if one is present, forces it on. This option is useful if your application does not use EMS explicitly, is not a resident program, and may be used with 386-based EMS simulator software.

0x04

directly pass down keyboard status calls -- When this option is set, status requests are passed down immediately and unconditionally. When disabled, pass-downs are limited so the 8042 auxiliary processor does not become overloaded by keyboard polling loops.

0x10

restore only changed interrupts -- Normally, when a DOS/4GW program terminates, all interrupts are restored to the values they had at the time of program startup. When you use this option, only the interrupts changed by the DOS/4GW program are restored.

0x20

set new memory to 00 -- When DOS/4GW allocates a new segment or increases the size of a segment, the memory is zeroed. This can help you find bugs having to do with uninitialized memory. You can also use it to provide a consistent working environment regardless of what programs were run earlier. This option only affects segment allocations or expansions that are made through the DOS/4GW kernel (with DOS function 48H or 4AH). This option does not affect memory allocated with a compiler's malloc function.

0x40

set new memory to FF -- When DOS/4GW allocates a new segment or increases the size of a segment, the memory is set to 0xFF bytes. This is helpful in making reproducible cases

of bugs caused by using uninitialized memory. This option only affects segment allocations or expansions that are made through the *DOS/4GW* kernel (with DOS function 48H or 4AH). This option does not affect memory allocated with a compiler's malloc function.

0x80

new selector rotation -- When DOS/4GW allocates a new selector, it usually looks for the first available (unused) selector in numerical order starting with the highest selector used when the program was loaded. When this option is set, the new selector search begins after the last selector that was allocated. This causes new selectors to rotate through the range. Use this option to find references to *stale* selectors, i.e., segments that have been cancelled or freed.

### 8.5 Controlling Address Line 20

This section explains how *DOS/4GW* uses address line 20 (A20) and describes the related **DOS16M** environment variable settings. It is unlikely that you will need to use these settings.

Because the 8086 and 8088 chips have 20-bit address spaces, their highest addressable memory location is one byte below 1MB. If you specify an address at 1MB or over, which would require a twenty-first bit to set, the address wraps back to zero. Some parts of DOS depend on this wrap, so on the 286 and 386, the twenty-first address bit is disabled. To address extended memory, *DOS/4GW* enables the twenty-first address bit (the A20 line). The A20 line must be enabled for the CPU to run in protected mode, but it may be either enabled or disabled in real mode.

By default, when *DOS/4GW* returns to real mode, it disables the A20 line. Some software depends on the line being enabled. *DOS/4GW* recognizes the most common software in this class, the XMS managers (such as HIMEM.SYS), and enables the A20 line when it returns to real mode if an XMS manager is present. For other software that requires the A20 line to be enabled, use the A20 option. The A20 option makes *DOS/4GW* restore the A20 line to the setting it had when *DOS/4GW* switched to protected mode. Set the environment variable as follows:

set DOS16M=A20

To specify more than one option on the command line, separate the options with spaces.

The **DOS16M** variable also lets you to specify the length of the delay between a *DOS/4GW* instruction to change the status of the A20 line and the next *DOS/4GW* operation. By default, this delay is 1 loop instruction when *DOS/4GW* is running on a 386 machine. In some cases, you may need to specify a longer delay for a machine that will run *DOS/4GW* but is not truly AT-compatible. To change the delay, set **DOS16M** to the desired number of loop instructions, preceded by a comma:

set DOS16M=, loops

### 9 vmm

The Virtual Memory Manager (VMM) uses a swap file on disk to augment RAM. With VMM you can use more memory than your machine actually has. When RAM is not sufficient, part of your program is swapped out to the disk file until it is needed again. The combination of the swap file and available RAM is the *virtual memory*.

Your program can use VMM if you set the DOS environment variable, **DOS4GVM**, as follows. To set the **DOS4GVM** environment variable, use the format shown below.

```
set DOS4GVM= [option[#value]] [option[#value]]
```

A "#" is used with options that take values since the DOS command shell will not accept "=".

If you set **DOS4GVM** equal to 1, the default parameters are used for all options.

Example:

C>set DOS4GVM=1

#### 9.1 VMM Default Parameters

VMM parameters control the options listed below.

**MINMEM** The minimum amount of RAM managed by VMM. The default is 512KB.

**MAXMEM** The maximum amount of RAM managed by VMM. The default is 4MB.

**SWAPMIN** The minimum or initial size of the swap file. If this option is not used, the size of the

swap file is based on VIRTUALSIZE (see below).

**SWAPINC** The size by which the swap file grows.

**SWAPNAME** The swap file name. The default name is "DOS4GVM.SWP". By default the file is in

the root directory of the current drive. Specify the complete path name if you want to

keep the swap file somewhere else.

**DELETESWAP** Whether the swap file is deleted when your program exits. By default the file is not

deleted. Program startup is quicker if the file is not deleted.

**VIRTUALSIZE** The size of the virtual memory space. The default is 16MB.

### 9.2 Changing the Defaults

You can change the defaults in two ways.

1. Specify different parameter values as arguments to the **DOS4GVM** environment variable, as shown in the example below.

```
set DOS4GVM=deleteswap maxmem#8192
```

2. Create a configuration file with the filetype extension ".VMC", and use that as an argument to the **DOS4GVM** environment variable, as shown below.

```
set DOS4GVM=@NEW4G.VMC
```

#### 9.2.1 The .VMC File

A ".VMC" file contains VMM parameters and settings as shown in the example below. Comments are permitted. Comments on lines by themselves are preceded by an exclamation point (!). Comments that follow option settings are preceded by white space. Do not insert blank lines: processing stops at the first blank line.

# 10 Interrupt 21H Functions

When you call an Interrupt 21H function under *DOS/4GW*, the 32-bit registers in which you pass values are translated into the appropriate 16-bit registers, since DOS works only with 16 bits. However, you can use 32-bit values in your DOS calls. You can allocate blocks of memory larger than 64KB or use an address with a 32-bit offset, and *DOS/4GW* will translate the call appropriately, to use 16-bit registers. When the Interrupt 21H function returns, the value is widened - placed in a 32-bit register, with the high order bits zeroed.

DOS/4GW uses the following rules to manage registers:

- When you pass a parameter to an Interrupt 21H function that expects a 16-bit quantity in a general register (for example, AX), pass a 32-bit quantity in the corresponding extended register (for example, EAX). When a DOS function returns a 16-bit quantity in a general register, expect to receive it (with high-order zero bits) in the corresponding extended register.
- When an Interrupt 21H function expects to receive a 16:16 pointer in a segment:general register pair (for example, ES:BX), supply a 16:32 pointer using the same segment register and the corresponding extended general register (ES:EBX). *DOS/4GW* will copy data and translate pointers so that DOS ultimately receives a 16:16 real-mode pointer in the correct registers.
- When DOS returns a 16:16 real-mode pointer, *DOS/4GW* translates the segment value into an appropriate protected-mode selector and generates a 32-bit offset that results in a 16:32 pointer to the same location in the linear address space.
- Many DOS functions return an error code in AX if the function fails. *DOS/4GW* checks the status of the carry flag, and if it is set, indicating an error, zero-extends the code for EAX. It does not change any other registers.
- If the value is passed or returned in an 8-bit register (AL or AH, for example), *DOS/4GW* puts the value in the appropriate location and leaves the upper half of the 32-bit register untouched.

The table below lists all the Interrupt 21h functions. For each, it shows the registers that are widened or narrowed. Footnotes provide additional information about some of the interrupts that require special handling. Following the table is a section that provides a detailed explanation of interrupt handling under *DOS/4GW*.

00H         Terminate Process         None           01H         Character Input with Echo         None           02H         Character Output         None           03H         Auxiliary Input         None           03H         Auxiliary Output         None           05H         Print Character         None           06H         Direct Console I/O         None           07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File	Function	Purpose	Managed Registers
02H         Character Output         None           03H         Auxiliary Input         None           04H         Auxiliary Output         None           05H         Print Character         None           06H         Direct Console I/O         None           07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0AH         Buffered Keyboard Input         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Open File with FCB         EDX           10H         Close File with FCB         EDX           10H         Close File with FCB         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Write         EDX           15H         Sequential Write	00H	Terminate Process	None
03H         Auxiliary Dutput         None           04H         Auxiliary Output         None           05H         Print Character         None           06H         Direct Console I/O         None           07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           08H         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Write         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX<	01H	Character Input with Echo	None
04H         Auxiliary Output         None           05H         Print Character         None           06H         Direct Console I/O         None           07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Read         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           10H         Creat File with FCB         EDX </td <td>02H</td> <td>Character Output</td> <td>None</td>	02H	Character Output	None
04H         Auxiliary Output         None           05H         Print Character         None           06H         Direct Console I/O         None           07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Read         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           10H         Creat File with FCB         EDX </td <td>03H</td> <td>Auxiliary Input</td> <td>None</td>	03H	Auxiliary Input	None
05H         Print Character         None           06H         Direct Console I/O         None           07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Write         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         Sex <td>04H</td> <td>• •</td> <td>None</td>	04H	• •	None
07H         Unfiltered Character Input Without Echo         None           08H         Character Input Without Echo         None           09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Write         EDX           15H         Sequential Write         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           19H         Get Default Drive Data         Returns in EBX, ECX, and EDX           10H         Get Default Drive Data         Returns in EBX, ECX, and EDX           21H <t< td=""><td>05H</td><td></td><td>None</td></t<>	05H		None
OSH Character Input Without Echo O9H Display String OAH Buffered Keyboard Input OBH Check Keyboard Input OBH Check Keyboard Status OBH Check Keyboard Status ODH Disk Reset ODH Disk Reset ODH Opisk Reset OPEN OPEN OPEN OPEN OPEN OPEN OPEN OPEN	06H	Direct Console I/O	None
OSH Character Input Without Echo O9H Display String OAH Buffered Keyboard Input OBH Check Keyboard Input OBH Check Keyboard Status OBH Check Keyboard Status ODH Disk Reset ODH Disk Reset ODH Opisk Reset OPEN OPEN OPEN OPEN OPEN OPEN OPEN OPEN	07H	Unfiltered Character Input Without	Echo None
09H         Display String         EDX           0AH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Write         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           1AH         Set DTA Address         EDX           1BH         Get Default Drive Data         Returns in EBX, ECX, and EDX           1CH         Get Drive Data         Returns in EBX, ECX, and EDX           21H         Random Read         EDX           22H         Random Write         EDX </td <td>08H</td> <td></td> <td></td>	08H		
OAH         Buffered Keyboard Input         EDX           0BH         Check Keyboard Status         None           0CH         Flush Buffer, Read Keyboard         EDX           0DH         Disk Reset         None           0EH         Select Disk         None           0FH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Write         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           1AH         Set DTA Address         EDX           1BH         Get Default Drive Data         Returns in EBX, ECX, and EDX           1CH         Get Drive Data         Returns in EBX, ECX, and EDX           23H         Get File Size         EDX           24H         Set Relative Record         EDX           25H         Set Interrupt Vector	09H	-	EDX
OBH         Check Keyboard Status         None           OCH         Flush Buffer, Read Keyboard         EDX           ODH         Disk Reset         None           OEH         Select Disk         None           OFH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Read         EDX           15H         Sequential Write         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           1AH         Set DTA Address         EDX           1BH         Get Default Drive Data         Returns in EBX, ECX, and EDX           1CH         Get Drive Data         Returns in EBX, ECX, and EDX           22H         Random Read         EDX           22H         Random Read         EDX           22H         Set Relative Record         EDX	0AH		EDX
OCH         Flush Buffer, Read Keyboard         EDX           ODH         Disk Reset         None           OEH         Select Disk         None           OFH         Open File with FCB         EDX           10H         Close File with FCB         EDX           11H         Find First File         EDX           12H         Find Next File         EDX           13H         Delete File         EDX           14H         Sequential Read         EDX           15H         Sequential Write         EDX           16H         Create File with FCB         EDX           17H         Rename File         EDX           19H         Get Current Disk         None           19H         Get Default Drive Data         Returns in EBX, ECX, and EDX           1BH         Get Default Drive Data         Returns in EBX, ECX, and EDX           21H         Random Read         EDX           22H         Random Write         EDX           23H         Get File Size         EDX           24H         Set Relative Record         EDX           25H         Set Interrupt Vector         EDX           26H         Create New Program Segment Prefix	0BH	• •	None
ODH       Disk Reset       None         0EH       Select Disk       None         0FH       Open File with FCB       EDX         10H       Close File with FCB       EDX         11H       Find First File       EDX         12H       Find Next File       EDX         13H       Delete File       EDX         14H       Sequential Write       EDX         15H       Sequential Write       EDX         16H       Create File with FCB       EDX         17H       Rename File       EDX         19H       Get Current Disk       None         1AH       Set DTA Address       EDX         1BH       Get Default Drive Data       Returns in EBX, ECX, and EDX         1CH       Get Drive Data       Returns in EBX, ECX, and EDX         2H       Random Read       EDX         22H       Random Write       EDX         23H       Get File Size       EDX         24H       Set Relative Record       EDX         25H       Retlative Record       EDX         26H       Create New Program Segment Prefix       None         27H       Random Block Write       EDX, returns in ECX			EDX
OEH       Select Disk       None         0FH       Open File with FCB       EDX         10H       Close File with FCB       EDX         11H       Find First File       EDX         12H       Find Next File       EDX         13H       Delete File       EDX         14H       Sequential Read       EDX         15H       Sequential Write       EDX         16H       Create File with FCB       EDX         17H       Rename File       EDX         19H       Get Current Disk       None         1AH       Set DTA Address       EDX         1BH       Get Default Drive Data       Returns in EBX, ECX, and EDX         1CH       Get Drive Data       Returns in EBX, ECX, and EDX         21H       Random Read       EDX         22H       Random Write       EDX         23H       Get File Size       EDX         24H       Set Relative Record       EDX         25H       Set Interrupt Vector       EDX         26H       Create New Program Segment Prefix       None         27H       Random Block Write       EDX, returns in ECX         29H       Parse Filename       ESI, EDI, returns in			None
10H Close File with FCB EDX 11H Find First File EDX 12H Find Next File EDX 13H Delete File EDX 13H Delete File EDX 14H Sequential Read EDX 15H Sequential Write EDX 17H Rename File EDX 17H Rename File EDX 17H Rename File EDX 17H Get Current Disk None 1AH Set DTA Address EDX 18H Get Default Drive Data Returns in EBX, ECX, and EDX 18H Get Drive Data Returns in EBX, ECX, and EDX 19H Gat Prive Data Returns in EBX, ECX, and EDX 19H Get Prive Data Returns in EDX, ECX, and EDX 19H Get Prive Data Returns in EDX, ECX, and EDX 19H Get File Size EDX 22H Random Write EDX 23H Get File Size EDX 24H Set Relative Record EDX 25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2CH Get Time None 2CH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX 30H Get/Set Control-C Check Flag None 33H Get/Set Control-C Check Flag Returns in EBX 36H Get Interrupt Vector Returns in EBX 36H Get Interrupt Vector Returns in EBX 36H Get Interrupt Vector Returns in EBX		Select Disk	None
10H Close File with FCB EDX 11H Find First File EDX 12H Find Next File EDX 13H Delete File EDX 13H Delete File EDX 14H Sequential Read EDX 15H Sequential Write EDX 17H Rename File EDX 17H Rename File EDX 17H Rename File EDX 17H Get Current Disk None 1AH Set DTA Address EDX 18H Get Default Drive Data Returns in EBX, ECX, and EDX 18H Get Drive Data Returns in EBX, ECX, and EDX 19H Gat Prive Data Returns in EBX, ECX, and EDX 19H Get Prive Data Returns in EDX, ECX, and EDX 19H Get Prive Data Returns in EDX, ECX, and EDX 19H Get File Size EDX 22H Random Write EDX 23H Get File Size EDX 24H Set Relative Record EDX 25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2CH Get Time None 2CH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX 30H Get/Set Control-C Check Flag None 33H Get/Set Control-C Check Flag Returns in EBX 36H Get Interrupt Vector Returns in EBX 36H Get Interrupt Vector Returns in EBX 36H Get Interrupt Vector Returns in EBX	0FH	Open File with FCB	EDX
11HFind First FileEDX12HFind Next FileEDX13HDelete FileEDX14HSequential ReadEDX15HSequential WriteEDX16HCreate File with FCBEDX17HRename FileEDX19HGet Current DiskNone1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone30HGet MS-DOS Version NumberReturns in EBX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX		1	
12HFind Next FileEDX13HDelete FileEDX14HSequential ReadEDX15HSequential WriteEDX16HCreate File with FCBEDX17HRename FileEDX19HGet Current DiskNone1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet OTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	10H	Close File with FCB	EDX
13HDelete FileEDX14HSequential ReadEDX15HSequential WriteEDX16HCreate File with FCBEDX17HRename FileEDX19HGet Current DiskNone1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in EBX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	11H	Find First File	EDX
14HSequential ReadEDX15HSequential WriteEDX16HCreate File with FCBEDX17HRename FileEDX19HGet Current DiskNone1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in EBX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	12H	Find Next File	EDX
15H Sequential Write EDX 16H Create File with FCB EDX 17H Rename File EDX 19H Get Current Disk None 1AH Set DTA Address EDX 18H Get Default Drive Data Returns in EBX, ECX, and EDX 1CH Get Drive Data Returns in EBX, ECX, and EDX 1CH Get Drive Data Returns in EBX, ECX, and EDX 22H Random Write EDX 23H Get File Size EDX 24H Set Relative Record EDX 25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2DH Set Time None 2FH Get DTA Address Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX	13H	Delete File	EDX
16HCreate File with FCBEDX17HRename FileEDX19HGet Current DiskNone1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	14H	Sequential Read	EDX
17HRename FileEDX19HGet Current DiskNone1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet OTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in EDX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	15H	Sequential Write	EDX
19H Get Current Disk None 1AH Set DTA Address EDX 1BH Get Default Drive Data Returns in EBX, ECX, and EDX 1CH Get Drive Data Returns in EBX, ECX, and EDX 21H Random Read EDX 22H Random Write EDX 23H Get File Size EDX 24H Set Relative Record EDX 25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2CH Get Time None 2DH Set Time None 2FH Get DTA Address Returns in ECX 30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX	16H	Create File with FCB	EDX
1AHSet DTA AddressEDX1BHGet Default Drive DataReturns in EBX, ECX, and EDX1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	17H	Rename File	EDX
1BH 1CHGet Default Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	19H	Get Current Disk	None
1CHGet Drive DataReturns in EBX, ECX, and EDX21HRandom ReadEDX22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	1AH	Set DTA Address	EDX
21H Random Read EDX 22H Random Write EDX 23H Get File Size EDX 24H Set Relative Record EDX 25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX 30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX	1BH	Get Default Drive Data	Returns in EBX, ECX, and EDX
22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	1CH	Get Drive Data	Returns in EBX, ECX, and EDX
22HRandom WriteEDX23HGet File SizeEDX24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	21H	Random Read	EDX
23H Get File Size EDX 24H Set Relative Record EDX 25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX 30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX	22H		EDX
24HSet Relative RecordEDX25HSet Interrupt VectorEDX26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX		Get File Size	
25H Set Interrupt Vector EDX 26H Create New Program Segment Prefix None 27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX 30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX		Set Relative Record	
26HCreate New Program Segment PrefixNone27HRandom Block ReadEDX, returns in ECX28HRandom Block WriteEDX, returns in ECX29HParse FilenameESI, EDI, returns in EAX, ESI and EDI (1.)2AHGet DateReturns in ECX2BHSet DateNone2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX			
27H Random Block Read EDX, returns in ECX 28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag Returns in EBX  36H Return Address of InDOS Flag Returns in EBX  37H Get Interrupt Vector Returns in EBX			
28H Random Block Write EDX, returns in ECX 29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag Returns in EBX  36H Return Address of InDOS Flag Returns in EBX  37H Get Interrupt Vector Returns in EBX			
29H Parse Filename ESI, EDI, returns in EAX, ESI and EDI (1.) 2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag 35H Get Interrupt Vector Returns in EBX			
2AH Get Date Returns in ECX 2BH Set Date None 2CH Get Time None 2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX  35H Get Interrupt Vector Returns in EBX			
2BH Set Date None 2CH Get Time None 2DH Set Time None 2DH Set/Reset Verify Flag None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX			
2CHGet TimeNone2DHSet TimeNone2EHSet/Reset Verify FlagNone2FHGet DTA AddressReturns in EBX30HGet MS-DOS Version NumberReturns in ECX31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX			
2DH Set Time None 2EH Set/Reset Verify Flag None 2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX			
2EH 2FHSet/Reset Verify Flag Get DTA AddressNone30H 31HGet MS-DOS Version Number Terminate and Stay Resident None 33H Get/Set Control-C Check Flag Return Address of InDOS Flag Get Interrupt VectorNone Returns in EBX Returns in EBX			None
2FH Get DTA Address Returns in EBX  30H Get MS-DOS Version Number Returns in ECX 31H Terminate and Stay Resident None 33H Get/Set Control-C Check Flag None 34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX			
31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX			
31HTerminate and Stay ResidentNone33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX	30H	Get MS-DOS Version Number	Returns in ECX
33HGet/Set Control-C Check FlagNone34HReturn Address of InDOS FlagReturns in EBX35HGet Interrupt VectorReturns in EBX			
34H Return Address of InDOS Flag Returns in EBX 35H Get Interrupt Vector Returns in EBX			
35H Get Interrupt Vector Returns in EBX			
•		=	
		=	

38H 39H 3AH 3BH 3CH 3DH 3EH 3FH	Get/Set Current Country Create Directory Remove Directory Change Current Directory Create File with Handle Open File with Handle Close File Read File or Device	EDX, returns in EBX EDX EDX EDX EDX EDX EDX, returns in EAX EDX, returns in EAX None EBX, ECX, EDX, returns in EAX (2.)
40H 41H 42H 43H 44H 00H 01H 02H 03H 04H 05H 06H 07H 08H 09H 0AH	Write File or Device Delete File Move File Pointer Get/Set File Attribute IOCTL Get Device Information SetDevice Information Read Control Data from CDD Write Control Data to CDD Read Control Data from BDD Write Control Data to BDD Check Input Status Check Output Status Check if Block Device is Removeable Check if Block Device is Remote Check if Handle is Remote	EBX, ECX, EDX, returns in EAX (2.)  EDX  Returns in EDX, EAX  EDX, returns in ECX  (3.)  Returns in EDX  None  EDX, returns in EAX  EDX, returns in EAX  EDX, returns in EAX  EDX, returns in EAX  None  None  Returns in EAX  Returns in EDX  Returns in EDX
0CH 0DH 0EH 0FH 45H 46H 47H	Generic I/O Control for Character Devices Generic I/O Control for Block Devices Get Logical Drive Map Set Logical Drive Map Duplicate File Handle Force Duplicate File Handle Get Current Directory	EDX EDX None None Returns in EAX None ESI
48H 49H 4AH 4BH 4CH 4DH 4EH 4FH	Allocate Memory Block Free Memory Block Resize Memory Block Load and Execute Program (EXEC) Terminate Process with Return Code Get Return Code of Child Process Find First File Find Next File	Returns in EAX None None EBX, EDX (4.) None None EDX None
52H 54H 56H 57H 58H 59H 5AH 5BH 5CH 5EH 00H 02H	Get List of Lists Get Verify Flag Rename File Get/Set Date/Time of File Get/Set Allocation Strategy Get Extended Error Information Create Temporary File Create New File Lock/Unlock File Region Network Machine Name/Printer Setup Get Machine Name Set Printer Setup String	(not supported) None EDX, EDI Returns in ECX, and EDX Returns in EAX Returns in EAX EDX, returns in EAX and EDX EDX, returns in EAX None EDX EDX

03H	Get Printer Setup String	EDI, returns in ECX
5FH	Get/Make Assign List Entry	
02H	Get Redirection List Entry	ESI, EDI, returns in ECX
03H	Redirect Device	ESI, EDI
04H	Cancel Device Redirection	ESI
62H	Get Program Segment Prefix Address	Returns in EBX
63H	Get Lead Byte Table (version 2.25 only)	Returns in ESI
65H	Get Extended Country Information	EDI
66H	Get or Set Code Page	None
67H	Set Handle Count	None

This list of functions is excerpted from *The MS-DOS Encyclopedia*, Copyright (c) 1988 by Microsoft Press. All Rights Reserved.

- 1. For Function 29H, DS:ESI and ES:EDI contain pointer values that are not changed by the call.
- You can read and write quantities larger than 64KB with Functions 3FH and 40H. DOS/4GW breaks your request into chunks smaller than 64KB, and calls the DOS function once for each chunk.
- You can't transfer more than 64KB using Function 44h, subfunctions 02H, 03H, 04H, or 05H.
   DOS/4GW does not break larger requests into DOS-sized chunks, as it does for Functions 3FH and 40H.
- 4. When you call Function 4B under *DOS/4GW*, you pass it a data structure that contains 16:32 bit pointers. *DOS/4GW* translates these into 16:16 bit pointers in the structure it passes to DOS.

# 10.1 Functions 25H and 35H: Interrupt Handling in Protected Mode

By default, interrupts that occur in protected mode are passed down: the entry in the IDT points to code in *DOS/4GW* that switches the CPU to real mode and resignals the interrupt. If you install an interrupt handler using Interrupt 21H, Function 25H, that handler will get control of any interrupts that occur while the processor is in protected mode. If the interrupt for which you installed the handler is in the *autopassup range*, your handler will also get control of interrupts signalled in real mode.

The autopassup range runs from 08H to 2EH inclusive, but excluding 21H. If the interrupt is in the autopassup range, the real-mode vector will be modified when you install the protected-mode handler to point to code in the *DOS/4GW* kernel. This code switches the processor to protected mode and resignals the interrupt-where your protected-mode handler will get control.

#### 10.1.1 32-Bit Gates

The *DOS/4GW* kernel always assigns a 32-bit gate for the interrupt handlers it installs. It does not distinguish between 16-bit and 32-bit handlers for consistency with DPMI.

This 32-bit gate points into the *DOS/4GW* kernel. When *DOS/4GW* handles the interrupt, it switches to its own 16-bit stack, and from there it calls the interrupt handler (yours or the default). This translation is

transparent to the handler, with one exception: since the current stack is not the one on which the interrupt occurred, the handler cannot look up the stack for the address at which the interrupt occurred.

### 10.1.2 Chaining 16-bit and 32-bit Handlers

If your program hooks an interrupt, write a normal service routine that either handles the interrupt and IRETs or chains to the previous handler. As part of handling the interrupt, your handler can PUSHF/CALL to the previous handler. The handler *must* IRET (or IRETD) or chain.

For each protected-mode interrupt, *DOS/4GW* maintains separate chains of 16-bit and 32-bit handlers. If your 16-bit handler chains, the previous handler is a 16-bit program. If your 32-bit handler chains, the previous handler is a 32-bit program.

If a 16-bit program hooks a given interrupt before any 32-bit programs hook it, the 16-bit chain is executed first. If all the 16-bit handlers unhook later and a new 16-bit program hooks the interrupt while 32-bit handlers are still outstanding, the 32-bit handlers will be executed first.

If the first program to hook an interrupt is 32-bit, the 32-bit chain is executed first.

### 10.1.3 Getting the Address of the Interrupt Handler

When you signal Interrupt 21H, Function 35, it always returns a non-null address even if no other program of your bitness (i.e., 16-bit or 32-bit) has hooked the interrupt. The address points to a dummy handler that looks to you as though it does an IRET to end the chain. This means that you can't find an unused interrupt by looking for a NULL pointer. Since this technique is most frequently used by programs that are looking for an unclaimed *real-mode* interrupt on which to install a TSR, it shouldn't cause you problems.

# 11 Interrupt 31H DPMI Functions

When a *DOS/4GW* application runs under a DPMI host, such as Windows 3.1 in enhanced mode, an OS/2 virtual DOS machine, 386Max (with DEBUG=DPMIXCOPY), or QEMM/QDPMI (with EXTCHKOFF), the DPMI host provides the DPMI services, not *DOS/4GW*. The DPMI host also provides virtual memory, if any. Performance (speed and memory use) under different DPMI hosts varies greatly due to the quality of the DPMI implementation.

DPMI services are accessed using Interrupt 31H.

The following describes the services provided by *DOS/4GW* and DOS/4GW Professional in the absence of a DPMI host. *DOS/4GW* supports many of the common DPMI system services. Not all of the services described below are supported by other DPMI hosts.

Some of the information in this chapter was obtained from the DOS Protected-Mode Interface (DPMI) specification. It is no longer in print; however the DPMI 1.0 specification can be obtained from the Intel ftp site. Here is the URL.

```
ftp://ftp.intel.com/pub/IAL/software_specs/dpmiv1.zip
```

This ZIP file contains a Postscript version of the DPMI 1.0 specification.

## 11.1 Using Interrupt 31H Function Calls

Interrupt 31H DPMI function calls can be used only by protected-mode programs.

The general ground rules for Interrupt 31H calls are as follows:

- All Interrupt 31H calls modify the AX register. Unsupported or unsuccessful calls return an error code in AX. Other registers are saved unless they contain specified return values.
- All Interrupt 31H calls modify flags: Unsupported or unsuccessful calls return with the carry flag set. Successful calls clear the carry flag. Only memory management and interrupt flag management calls modify the interrupt flag.
- Memory management calls can enable interrupts.
- All calls are reentrant.

The flag and register information for each call is listed in the following descriptions of supported Interrupt 31H function calls.

### 11.2 Int31H Function Calls

The Interrupt 31H subfunction calls supported by *DOS/4GW* are listed below by category:

- Local Descriptor Table (LDT) management services
- DOS memory management services
- Interrupt services
- Translation services
- DPMI version
- Memory management services
- Page locking services
- Demand paging performance tuning services
- · Physical address mapping
- Virtual interrupt state functions
- Vendor specific extensions
- Coprocessor status

Only the most commonly used Interrupt 31H function calls are supported in this version.

## 11.2.1 Local Descriptor Table (LDT) Management Services

**Function 0000H** This function allocates a specified number of descriptors from the LDT and returns the base selector. Pass the following information:

AX = 0000H

**CX** = number of descriptors to be allocated

If the call succeeds, the carry flag is clear and the base selector is returned in AX. If the call fails, the carry flag is set.

An allocated descriptor is set to the present data type, with a base and limit of zero. The privilege level of an allocated descriptor is set to match the code segment privilege level of the application. To find out the privilege level of a descriptor, use the lar instruction.

Allocated descriptors must be filled in by the application. If more than one descriptor is allocated, the returned selector is the first of a contiguous array. Use Function 0003H to get the increment for the next selector in the array.

Function 0001H This function frees the descriptor specified. Pass the following information:

AX = 0001H

**BX** = the selector to free

Use the selector returned with function 0000h when the descriptor was allocated. To free an array of descriptors, call this function for each descriptor. Use Function 0003H to find out the increment for each descriptor in the array.

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

You can use this function to free the descriptors allocated for the program's initial CS, DS, and SS segments, but you should not free other segments that were not allocated with Function 0000H or Function 000DH.

**Function 0002H** This function converts a real-mode segment to a descriptor that a protected-mode program can address. Pass the following information:

AX = 0002H

BX = real-mode segment address

If the call succeeds, it clears the carry flag and returns the selector mapped to the real-mode segment in AX. If the call fails, the carry flag is set.

If you call this function more than once with the same real-mode segment address, you get the same selector value each time. The descriptor limit is set to 64KB.

The purpose of this function is to give protected-mode programs easy access to commonly used real-mode segments. However, because you cannot modify or free descriptors created by this function, it should be used infrequently. Do not use this function to get descriptors for private data areas.

To examine real-mode addresses using the same selector, first allocate a descriptor, and then use Function 0007H to change the linear base address.

**Function 0003H** This function returns the increment value for the next selector. Use this function to get the value you add to the base address of an allocated array of descriptors to get the next selector address. Pass the following information:

AX = 0003H

This call always succeeds. The increment value is returned in AX. This value is always a power of two, but no other assumptions can be made.

Function 0006H This function gets the linear base address of a selector. Pass the following information:

 $\mathbf{AX} = \mathbf{0006H}$ 

BX = selector

If the call succeeds, the carry flag is clear and CX:DX contains the 32-bit linear base address of the segment. If the call fails, it sets the carry flag.

If the selector you specify in BX is invalid, the call fails.

**Function 0007H** This function changes the base address of a specified selector. Only descriptors allocated through Function 0000H should be modified. Pass the following information:

 $\mathbf{AX} = \mathbf{0007H}$ 

BX = selector

CX:DX = the new 32-bit linear base address for the segment

If the call succeeds, the carry flag is clear; if unsuccessful, the carry flag is set.

If the selector you specify in BX is invalid, the call fails.

**Function 0008H** This function sets the upper limit of a specified segment. Use this function to modify descriptors allocated with Function 0000H only. Pass the following information:

AX = 0008H

BX = selector

CX:DX = 32-bit segment limit

If the call succeeds, the carry flag is clear; if unsuccessful, the carry flag is set.

The call fails if the specified selector is invalid, or if the specified limit cannot be set.

Segment limits greater than 1MB must be page-aligned. This means that limits greater than 1MB must have the low 12 bits set.

To get the limit of a segment, use the 32-bit form of lsl for segment limits greater than 64KB.

**Function 0009H** This function sets the descriptor access rights. Use this function to modify descriptors allocated with Function 0000H only. To examine the access rights of a descriptor, use the lar instruction. Pass the following information:

AX = 0009H

BX = selector

CL = Access rights/type byte

CH = 386 extended access rights/type byte

If the call succeeds, the carry flag is clear; if unsuccessful, the carry flag is set. If the selector you specify in BX is invalid, the call fails. The call also fails if the access rights/type byte does not match the format and meet the requirements shown in the figures below.



The access rights/type byte passed in CL has the format shown in the figure below.

Figure 3. Access Rights/Type



The extended access rights/type byte passed in CH has the following format.

Figure 4. Extended Access Rights/Type

**Function 000AH** This function creates an alias to a code segment. This function creates a data descriptor that has the same base and limit as the specified code segment descriptor. Pass the following information:

AX = 000AH BX = code segment selector

If the call succeeds, the carry flag is clear and the new data selector is returned in AX. If the call fails, the carry flag is set. The call fails if the selector passed in BX is not a valid code segment.

To deallocate an alias to a code segment, use Function 0001H.

After the alias is created, it does not change if the code segment descriptor changes. For example, if the base or limit of the code segment change later, the alias descriptor stays the same.

**Function 000BH** This function copies the descriptor table entry for a specified descriptor. The copy is written into an 8-byte buffer. Pass the following information:

 $\mathbf{AX} = \mathbf{000BH}$ 

BX = selector

ES:EDI = a pointer to the 8-byte buffer for the descriptor copy

If the call succeeds, the carry flag is clear and ES:EDI contains a pointer to the buffer that contains a copy of the descriptor. If the call fails, the carry flag is set. The call fails if the selector passed in BX is invalid or unallocated.

**Function 000CH** This function copies an 8-byte buffer into the LDT for a specified descriptor. The descriptor must first have been allocated with Function 0000H. Pass the following information:

AX = 000CH

BX = selector

ES:EDI = a pointer to the 8-byte buffer containing the descriptor

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set. The call fails if the descriptor passed in BX is invalid.

The type byte, byte 5, has the same format and requirements as the access rights/type byte passed to Function 0009H in CL. The format is shown in the first figure presented with the description of Function 0009H.

The extended type byte, byte 6, has the same format and requirements as the extended access rights/type byte passed to Function 0009H in CH, except that the limit field can have any value, and the low order bits marked *reserved* are used to set the upper 4 bits of the descriptor limit. The format is shown in the second figure presented with the description of Function 0009H.

Function 000DH This function allocates a specific LDT descriptor. Pass the following information:

AX = 000DH BX = selector

If the call succeeds, the carry flag is clear and the specified descriptor is allocated. If the call fails, the carry flag is set.

The call fails if the specified selector is already in use, or if it is not a valid LDT descriptor. The first 10h (16 decimal) descriptors are reserved for this function, and should not be used by the host. Some of these descriptors may be in use, however, if another client application is already loaded.

To free the descriptor, use Function 0001H.

### 11.2.2 DOS Memory Management Services

**Function 0100H** This function allocates memory from the DOS free memory pool. This function returns both the real-mode segment and one or more descriptors that can be used by protected-mode applications. Pass the following information:

AX = 0100H

BX = the number of paragraphs (16-byte blocks) requested

If the call succeeds, the carry flag is clear. AX contains the initial real-mode segment of the allocated block and DX contains the base selector for the allocated block.

If the call fails, the carry flag is set. AX contains the DOS error code. If memory is damaged, code 07H is returned. If there is not enough memory to satisfy the request, code 08H is returned. BX contains the number of paragraphs in the largest available block of DOS memory.

If you request a block larger than 64KB, contiguous descriptors are allocated. Use Function 0003H to find the value of the increment to the next descriptor. The limit of the first descriptor is set to the entire block. Subsequent descriptors have a limit of 64KB, except for the final descriptor, which has a limit of blocksize MOD 64KB.

You cannot modify or deallocate descriptors allocated with this function. Function 101H deallocates the descriptors automatically.

**Function 0101H** This function frees a DOS memory block allocated with function 0100H. Pass the following information:

AX = 0101H

DX = selector of the block to be freed

If the call succeeds, the carry flag is clear.

If the call fails, the carry flag is set and the DOS error code is returned in AX. If the incorrect segment was specified, code 09H is returned. If memory control blocks are damaged, code 07H is returned.

All descriptors allocated for the specified memory block are deallocated automatically and cannot be accessed correctly after the block is freed.

**Function 0102H** This function resizes a DOS memory block allocated with function 0100H. Pass the following information:

AX = 0102H

BX = the number of paragraphs (16-byte blocks) in the resized block

DX = selector of block to resize

If the call succeeds, the carry flag is clear.

If the call fails, the carry flag is set, the maximum number of paragraphs available is returned in BX, and the DOS error code is returned in AX. If memory code blocks are damaged, code 07H is returned. If there isn't enough memory to increase the size as requested, code 08H is returned. If the incorrect segment is specified, code 09h is returned.

Because of the difficulty of finding additional contiguous memory or descriptors, this function is not often used to increase the size of a memory block. Increasing the size of a memory block might well fail because other DOS allocations have used contiguous space. If the next descriptor in the LDT is not free, allocation also fails when the size of a block grows over the 64KB boundary.

If you shrink the size of a memory block, you may also free some descriptors allocated to the block. The initial selector remains unchanged, however; only the limits of subsequent selectors will change.

### 11.2.3 Interrupt Services

**Function 0200H** This function gets the value of the current task's real-mode interrupt vector for the specified interrupt. Pass the following information:

AX = 0200H

**BL** = interrupt number

This call always succeeds. All 100H (256 decimal) interrupt vectors are supported by the host. When the call returns, the carry flag is clear, and the segment:offset of the real-mode interrupt handler is returned in CX:DX.

Because the address returned in CX is a segment, and not a selector, you cannot put it into a protected-mode segment register. If you do, a general protection fault may occur.

**Function 0201H** This function sets the value of the current task's real-mode interrupt vector for the specified interrupt. Pass the following information:

AX = 0201H

**BL** = interrupt number

CX:DX = segment:offset of the real-mode interrupt handler

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

The address passed in CX:DX should be a real-mode segment:offset, such as function 0200H returns. For this reason, the interrupt handler must reside in DOS addressable memory. You can use Function 0100H to allocate DOS memory. This version does not support the real-mode callback address function.

If you are hooking a hardware interrupt, you have to lock all segments involved. These segments include the segment in which the interrupt handler runs, and any segment it may touch at interrupt time.

Function 0202H This function gets the processor exception handler vector. This function returns the CS:EIP of the current protected-mode exception handler for the specified exception number. Pass the following information:

AX = 0202H

BL = exception/fault number (00h - 1Fh)

If the call succeeds, the carry flag is clear and the selector:offset of the protected-mode exception handler is returned in CX:EDX. If it fails, the carry flag is set.

The value returned in CX is a valid protected-mode selector, not a real-mode segment.

Function 0203H This function sets the processor exception handler vector. This function allows protected-mode applications to intercept processor exceptions that are not handled by the DPMI environment. Programs may wish to handle exceptions such as "not present segment faults" which would otherwise generate a fatal error. Pass the following information:

AX = 0203H

BL = exception/fault number (00h - 1Fh)

CX:EDX = selector:offset of the exception handler

If the call succeeds, the carry flag is clear. If it fails, the carry flag is set.

The address passed in CX must be a valid protected-mode selector, such as Function 204H returns, and not a real-mode segment. A 32-bit implementation must supply a 32-bit offset in the EDX register. If the handler chains to the next handler, it must use a 32-bit interrupt stack frame to do so.

The handler should return using a far return instruction. The original SS:ESP, CS:EIP and flags on the stack, including the interrupt flag, will be restored.

All fault stack frames have an error code. However the error code is only valid for exceptions 08h, 0Ah, 0Bh, 0Ch, 0Dh, and 0Eh.

The handler must preserve and restore all registers.

The exception handler will be called on a locked stack with interrupts disabled. The original SS, ESP, CS, and EIP will be pushed on the exception handler stack frame.

The handler must either return from the call by executing a far return or jump to the next handler in the chain (which will execute a far return or chain to the next handler).

The procedure can modify any of the values on the stack pertaining to the exception before returning. This can be used, for example, to jump to a procedure by modifying the CS:EIP on the stack. Note that the procedure must not modify the far return address on the stack it must return to the original caller. The caller will then restore the flags, CS:EIP and SS:ESP from the stack frame.

If the DPMI client does not handle an exception, or jumps to the default exception handler, the host will reflect the exception as an interrupt for exceptions 0, 1, 2, 3, 4, 5 and 7. Exceptions 6 and 8 - 1Fh will be treated as fatal errors and the client will be terminated.

Exception handlers will only be called for exceptions that occur in protected mode.

Function 0204H This function gets the CS:EIP selector: offset of the current protected-mode interrupt handler for a specified interrupt number. Pass the following information:

AX = 0204H

**BL** = interrupt number

This call always succeeds. All 100H (256 decimal) interrupt vectors are supported by the host. When the call returns, the carry flag is clear and CX:EDX contains the protected-mode selector:offset of the exception handler.

A 32-bit offset is returned in the EDX register.

Function 0205H This function sets the address of the specified protected-mode interrupt vector. Pass the following information:

AX = 0205H

**BL** = interrupt number

**CX:EDX** = selector:offset of the exception handler

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

The address passed in CX must be a valid protected-mode selector, such as Function 204H returns, and not a real-mode segment. A 32-bit implementation must supply a 32-bit offset in the EDX register. If the handler chains to the next handler, it must use a 32-bit interrupt stack frame to do so.

### 11.2.4 Translation Services

These services are provided so that protected-mode programs can call real-mode software that DPMI does not support directly. The protected-mode program must set up a data structure with the appropriate register values. This "real-mode call structure" is shown below.

Offset	Register
00H	EDI
04H	ESI
08H	EBP
0CH	Reserved by system
10H	EBX
14H	EDX
18H	ECX
1CH	EAX
20H	Flags
22H	ES
24H	DS
26Н	FS
28H	GS
2AH	IP
2CH	CS
2EH	SP
30H	SS

After the call or interrupt is complete, all real-mode registers and flags except SS, SP, CS, and IP will be copied back to the real-mode call structure so that the caller can examine the real-mode return values.

The values in the segment registers should be real-mode segments, not protected-mode selectors.

The translation services will provide a real-mode stack if the SS:SP fields are zero. However, the stack provided is relatively small. If the real-mode procedure/interrupt routine uses more than 30 words of stack space then you should provide your own real-mode stack.

**Function 0300H** This function simulates a real-mode interrupt. This function simulates an interrupt in real mode. It will invoke the CS:IP specified by the real-mode interrupt vector and the handler must return by executing an iret. Pass the following information:

AX = 0300H

**BL** = interrupt number

**BH = flags** Bit 0 = 1 resets the interrupt controller and A20 line. Other flags are reserved and must be 0.

CX = number of words to copy from protected-mode stack to real-mode stack ES:EDI = the selector:offset of real-mode call structure

If the call fails, the carry flag is set.

If the call succeeds, the carry flag is clear and ES:EDI contains the selector:offset of the modified real-mode call structure.

The CS:IP in the real-mode call structure is ignored by this service. The appropriate interrupt handler will be called based on the value passed in BL.

The flags specified in the real-mode call structure will be pushed on the real-mode stack iret frame. The interrupt handler will be called with the interrupt and trace flags clear.

It is up to the caller to remove any parameters that were pushed on the protected-mode stack.

The flag to reset the interrupt controller and the A20 line is ignored by DPMI implementations that run in Virtual 8086 mode. It causes DPMI implementations that return to real mode to set the interrupt controller and A20 address line hardware to its normal real-mode state.

**Function 0301H** (DOS/4GW Professional only) This function calls a real-mode procedure with a FAR return frame. The called procedure must execute a FAR return when it completes. Pass the following information:

AX = 0301H

**BH = flags** Bit 0 = 1 resets the interrupt controller and A20 line. Other flags reserved and must be 0.

CX = Number of words to copy from protected-mode to real-mode stack ES:EDI = selector:offset of real-mode call structure

If the call succeeds, the carry flag is clear and ES:EDI contains the selector:offset of modified real-mode call structure.

If the call fails, the carry flag is set.

#### Notes:

- 1. The CS:IP in the real-mode call structure specifies the address of the real-mode procedure to call.
- 2. The real-mode procedure must execute a FAR return when it has completed.
- 3. If the SS:SP fields are zero then a real-mode stack will be provided by the DPMI host. Otherwise, the real-mode SS:SP will be set to the specified values before the procedure is called.
- 4. When the Int 31h returns, the real-mode call structure will contain the values that were returned by the real-mode procedure.

- It is up to the caller to remove any parameters that were pushed on the protected-mode stack.
- The flag to reset the interrupt controller and A20 line is ignored by DPMI implementations that run in Virtual 8086 mode. It causes DPMI implementations that return to real mode to set the interrupt controller and A20 address line hardware to its normal real-mode state.

Function 0302H (DOS/4GW Professional only) This function calls a real-mode procedure with an iret frame. The called procedure must execute an iret when it completes. Pass the following information:

AX = 0302H

BH = flagsBit 0 = 1 resets the interrupt controller and A20 line. Other flags reserved and must be 0.

CX = Number of words to copy from protected-mode to real-mode stack ES:EDI = selector:offset of real-mode call structure

If the call succeeds, the carry flag is clear and ES:EDI contains the selector:offset of modified real-mode call structure.

If the call fails, the carry flag is set.

#### Notes:

- The CS:IP in the real-mode call structure specifies the address of the real-mode procedure to call.
- The real-mode procedure must execute an iret when it has completed.
- If the SS:SP fields are zero then a real-mode stack will be provided by the DPMI host. Otherwise, the real-mode SS:SP will be set to the specified values before the procedure is called.
- When the Int 31h returns, the real-mode call structure will contain the values that were returned by the real-mode procedure.
- The flags specified in the real-mode call structure will be pushed the real-mode stack iret frame. The procedure will be called with the interrupt and trace flags clear.
- It is up to the caller to remove any parameters that were pushed on the protected-mode stack.
- The flag to reset the interrupt controller and A20 line is ignored by DPMI implementations that run in Virtual 8086 mode. It causes DPMI implementations that return to real mode to set the interrupt controller and A20 address line hardware to its normal real-mode state.

Function 0303H (DOS/4GW Professional only) This function allocates a real-mode callback address. This service is used to obtain a unique real-mode SEG:OFFSET that will transfer control from real mode to a protected-mode procedure.

At times it is necessary to hook a real-mode interrupt or device callback in a protected-mode driver. For example, many mouse drivers call an address whenever the mouse is moved. Software running in protected mode can use a real-mode callback to intercept the mouse driver calls. Pass the following information:

AX = 0303H

DS:ESI = selector:offset of procedure to call ES:EDI = selector:offset of real-mode call structure

If the call succeeds, the carry flag is clear and CX:DX contains the segment:offset of real-mode callback address.

If the call fails, the carry flag is set.

#### Callback Procedure Parameters

Interrupts disabled
DS:ESI = selector:offset of real-mode SS:SP
ES:EDI = selector:offset of real-mode call structure
SS:ESP = Locked protected-mode API stack
All other registers undefined

#### Return from Callback Procedure

Execute an IRET to return
ES:EDI = selector:offset of real-mode call structure
to restore (see note)

#### Notes:

- Since the real-mode call structure is static, you must be careful when writing
  code that may be reentered. The simplest method of avoiding reentrancy is to
  leave interrupts disabled throughout the entire call. However, if the amount of
  code executed by the callback is large then you will need to copy the real-mode
  call structure into another buffer. You can then return with ES:EDI pointing to
  the buffer you copied the data to it does not have to point to the original real
  mode call structure.
- 2. The called procedure is responsible for modifying the real-mode CS:IP before returning. If the real-mode CS:IP is left unchanged then the real-mode callback will be executed immediately and your procedure will be called again. Normally you will want to pop a return address off of the real-mode stack and place it in the real-mode CS:IP. The example code in the next section demonstrates chaining to another interrupt handler and simulating a real-mode iret.
- 3. To return values to the real-mode caller, you must modify the real-mode call structure.
- 4. Remember that all segment values in the real-mode call structure will contain real-mode segments, not selectors. If you need to examine data pointed to by a real-mode seg:offset pointer, you should not use the segment to selector service to create a new selector. Instead, allocate a descriptor during initialization and change the descriptor's base to 16 times the real-mode segment's value. This is

important since selectors allocated though the segment to selector service can never be freed.

5. DPMI hosts should provide a minimum of 16 callback addresses per task.

The following code is a sample of a real-mode interrupt hook. It hooks the DOS Int 21h and returns an error for the delete file function (AH=41h). Other calls are passed through to DOS. This example is somewhat silly but it demonstrates the techniques used to hook a real mode interrupt. Note that since DOS calls are reflected from protected mode to real mode, the following code will intercept all DOS calls from both real mode and protected mode.

```
; This procedure gets the current Int 21h real-mode \,
; Seg:Offset, allocates a real-mode callback address,
; and sets the real-mode Int 21h vector to the call-
; back address.
Initialization_Code:
; Create a code segment alias to save data in
                                                                   ax, 000Ah
                                  mov
                                  mov
                                                                   bx, cs
                                                                    31h
                                  int
                                                                   ERROR
                                  jс
                                  mov
                                                                    ds, ax
                                  ASSUMES DS,_TEXT
      Get current Int 21h real-mode SEG:OFFSET
                                  mov
                                                                   ax, 0200h
                                                                   bl, 21h
                                  mov
                                  int
                                                                    31h
                                                                   ERROR
                                  iс
                                                                    [Orig_Real_Seg], cx
                                  mov
                                  mov
                                                                    [Orig_Real_Offset], dx
; Allocate a real-mode callback
                                  mov
                                                                    ax, 0303h
                                  push
                                                                   ds
                                  mov
                                                                   bx, cs
                                  mov
                                                                    ds, bx
                                                                    si, OFFSET My_Int_21_Hook
                                  mov
                                                                    di, OFFSET My_Real_Mode_Call_Struc
                                  mov
                                  int
                                                                    31h
                                                                    ERROR
                                  jс
; Hook real-mode int 21h with the callback address
                                                                    ax, 0201h
                                  mov
                                                                   bl, 21h
                                  mov
                                                                   31h
                                  int
                                                                    ERROR
                                  jс
; This is the actual Int 21h hook code. It will return
     an "access denied" error for all calls made in real
; mode to delete a file. Other calls will be passed
; through to DOS.
; ENTRY:
                   DS:SI -> Real-mode SS:SP
                    ES:DI -> Real-mode call structure
                    Interrupts disabled
; EXIT:
                    ES:DI -> Real-mode call structure
My_Int_21_Hook:
                               cmp es:[di.RealMode_AH], 41h
                                                                  Chain_To_DOS
                                  jne
; This is a delete file call (AH=41h). Simulate an
; iret on the real-mode stack, set the real-mode % \left( 1\right) =\left( 1\right) \left( 1\right) +\left( 1\right) \left( 1\right) \left( 1\right) +\left( 1\right) \left( 1\right) \left(
; carry flag, and set the real-mode AX to 5 to indicate
; an access denied error.
```

```
cld
                             ; Get real-mode ret IP
       lodsw
               es:[di.RealMode_IP], ax
       mov
       lodsw
                       ; Get real-mode ret CS
               es:[di.RealMode_CS], ax
       mov
                      ; Get real-mode flags
       lodsw
                               ; Set carry flag
               ax. 1
       or
               es:[di.RealMode_Flags], ax
       mov
       add
               es:[di.RealMode_SP], 6
       mov
               es:[di.RealMode_AX], 5
        jmp
               My_Hook_Exit
; Chain to original Int 21h vector by replacing the
; real-mode CS:IP with the original Seg:Offset.
Chain_To_DOS:
              ax, cs:[Orig_Real_Seg]
       mov
             es:[di.RealMode_CS], ax
              ax, cs:[Orig_Real_Offset]
       mov
       mov
               es:[di.RealMode_IP], ax
My_Hook_Exit:
       iret
```

**Function 0304H** (DOS/4GW Professional only) This function frees a real-mode callback address that was allocated through the allocate real-mode callback address service. Pass the following information:

#### AX = 0304H

#### CX:DX = Real-mode callback address to free

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

Notes:

 Real-mode callbacks are a limited resource. Your code should free any break point that it is no longer using.

#### 11.2.5 DPMI Version

**Function 0400H** This function returns the version of DPMI services supported. Note that this is not necessarily the version of any operating system that supports DPMI. It should be used by programs to determine what calls are legal in the current environment. Pass the following information:

#### AX = 0400H

The information returned is:

```
AH = Major version
```

**AL = Minor version** 

**BX = Flags** Bit 0 = 1 if running under an 80386 DPMI implementation. Bit 1 = 1 if processor is returned to real mode for reflected interrupts (as opposed to Virtual 8086 mode). Bit 2 = 1 if virtual memory is supported. Bit 3 is reserved and undefined. All other bits are zero and reserved for later use.

**CL** = **Processor** type

02 = 80286

03 = 80386

04 = 80486

05 = Pentium

DH = Current value of virtual master PIC base interrupt DL = Current value of virtual slave PIC base interrupt

Carry flag clear (call cannot fail)

### 11.2.6 Memory Management Services

Function 0500H This function gets information about free memory. Pass the following information:

AX = 0500H

ES:EDI = the selector:offset of a 30H byte buffer.

If the call fails, the carry flag is set.

If the call succeeds, the carry flag is clear and ES:EDI contains the selector:offset of a buffer with the structure shown in the figure below.

Offset	Description
00H	Largest available block, in bytes
04H	Maximum unlocked page allocation
08H	Largest block of memory (in pages) that could be allocated and then locked
0СН	Total linear address space size, in pages, including already allocated pages
10H	Total number of free pages and pages currently unlocked and available for paging out
14H	Number of physical pages not in use
18H	Total number of physical pages managed by host
1CH	Free linear address space, in pages
20H	Size of paging/file partition, in pages
24H - 2FH	Reserved

Only the first field of the structure is guaranteed to contain a valid value. Any field that is not returned by *DOS/4GW* is set to -1 (0FFFFFFFH).

Function 0501H This function allocates and commits linear memory. Pass the following information:

AX = 0501H

**BX:CX** = size of memory to allocate, in bytes.

If the call succeeds, the carry flag is clear, BX:CX contains the linear address of the allocated memory, and SI:DI contains the memory block handle used to free or resize the block. If the call fails, the carry flag is set.

No selectors are allocated for the memory block. The caller must allocate and initialize selectors needed to access the memory.

If VMM is present, the memory is allocated as unlocked, page granular blocks. Because of the page granularity, memory should be allocated in multiples of 4KB.

Function 0502H This function frees a block of memory allocated through function 0501H. Pass the following information:

AX = 0502H

SI:DI = handle returned with function 0501H when memory was allocated

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set. You must also free any selectors allocated to point to the freed memory block.

Function 0503H This function resizes a block of memory allocated through the 0501H function. If you resize a block of linear memory, it may have a new linear address and a new handle. Pass the following information:

AX = 0503H

BX:CX = new size of memory block, in bytes

SI:DI = handle returned with function 0501H when memory was allocated

If the call succeeds, the carry flag is clear, BX:CX contains the new linear address of the memory block, and SI:DI contains the new handle of the memory block. If the call fails, the carry flag is set.

If either the linear address or the handle has changed, update the selectors that point to the memory block. Use the new handle instead of the old one.

You cannot resize a memory block to zero bytes.

### 11.2.7 Page Locking Services

These services are only useful under DPMI implementations that support virtual memory. Although memory ranges are specified in bytes, the actual unit of memory that will be locked will be one or more pages. Page locks are maintained as a count. When the count is decremented to zero, the page is unlocked and can be swapped to disk. This means that if a region of memory is locked three times then it must be unlocked three times before the pages will be unlocked.

Function 0600H This function locks a specified linear address range. Pass the following information:

AX = 0600H

BX:CX = starting linear address of memory to lock SI:DI = size of region to lock (in bytes)

If the call fails, the carry flag is set and none of the memory will be locked.

If the call succeeds, the carry flag is clear. If the specified region overlaps part of a page at the beginning or end of a region, the page(s) will be locked.

**Function 0601H** This function unlocks a specified linear address range that was previously locked using the "lock linear region" function (0600h). Pass the following information:

AX = 0601H

BX:CX = starting linear address of memory to unlock SI:DI = size of region to unlock (in bytes)

If the call fails, the carry flag is set and none of the memory will be unlocked. An error will be returned if the memory was not previously locked or if the specified region is invalid.

If the call succeeds, the carry flag is clear. If the specified region overlaps part of a page at the beginning or end of a region, the page(s) will be unlocked. Even if the call succeeds, the memory will remain locked if the lock count is not decremented to zero.

**Function 0604H** This function gets the page size for Virtual Memory (VM) only. This function returns the size of a single memory page in bytes. Pass the following information:

AX = 0604H

If the call succeeds, the carry flag is clear and BX:CX = Page size in bytes.

If the call fails, the carry flag is set.

### 11.2.8 Demand Paging Performance Tuning Services

Some applications will discard memory objects or will not access objects for long periods of time. These services can be used to improve the performance of demand paging.

Although these functions are only relevant for DPMI implementations that support virtual memory, other implementations will ignore these functions (it will always return carry clear). Therefore your code can always call these functions regardless of the environment it is running under.

Since both of these functions are simply advisory functions, the operating system may choose to ignore them. In any case, your code should function properly even if the functions fail.

Function 0702H (DOS/4GW Professional only) This function marks a page as a demand paging candidate. This function is used to inform the operating system that a range of pages should be placed at the head of the page out candidate list. This will force these pages to be swapped to disk ahead of other pages even if the memory has been accessed recently. However, all memory contents will be preserved.

This is useful, for example, if a program knows that a given piece of data will not be accessed for a long period of time. That data is ideal for swapping to disk since the physical memory it now occupies can be used for other purposes. Pass the following information:

AX = 0702H

BX:CX = Starting linear address of pages to mark SI:DI = Number of bytes to mark as paging candidates

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

Notes:

- 1. This function does not force the pages to be swapped to disk immediately.
- 2. Partial pages will not be discarded.

**Function 0703H** (DOS/4GW Professional only) This function discards page contents. This function discards the entire contents of a given linear memory range. It is used after a memory object that occupied a given piece of memory has been discarded.

The contents of the region will be undefined the next time the memory is accessed. All values previously stored in this memory will be lost. Pass the following information:

AX = 0703H

BX:CX = Starting linear address of pages to discard SI:DI = Number of bytes to discard

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

Notes:

1. Partial pages will not be discarded.

### 11.2.9 Physical Address Mapping

Memory mapped devices such as network adapters and displays sometimes have memory mapped at physical addresses that lie outside of the normal 1Mb of memory that is addressable in real mode. Under many implementations of DPMI, all addresses are linear addresses since they use the paging mechanism of the 80386. This service can be used by device drivers to convert a physical address into a linear address. The linear address can then be used to access the device memory.

Function 0800H This function is used for Physical Address Mapping.

Some implementations of DPMI may not support this call because it could be used to circumvent system protection. This call should only be used by programs that absolutely require direct access to a memory mapped device.

Pass the following information:

AX = 0800H BX:CX = Physical address of memory SI:DI = Size of region to map in bytes

If the call succeeds, the carry flag is clear and BX:CX = Linear Address that can be used to access the physical memory.

If the call fails, the carry flag is set.

#### Notes:

- Under DPMI implementations that do not use the 80386 paging mechanism, the call will always succeed and the address returned will be equal to the physical address parameter passed into this function.
- 2. It is up to the caller to build an appropriate selector to access the memory.
- 3. Do not use this service to access memory that is mapped in the first megabyte of address space (the real-mode addressable region).

Function 0801H This function is used to free Physical Address Mapping. Pass the following information:

AX = 0801H BX:CX = Linear address returned by Function 0800H.

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

#### Notes:

1. The client should call this function when it is finished using a device previously mapped to linear addresses with the Physical Address Mapping function (Function 0800H).

### 11.2.10 Virtual Interrupt State Functions

Under many implementations of DPMI, the interrupt flag in protected mode will always be set (interrupts enabled). This is because the program is running under a protected operating system that cannot allow programs to disable physical hardware interrupts. However, the operating system will maintain a "virtual" interrupt state for protected-mode programs. When the program executes a CLI instruction, the program's virtual interrupt state will be disabled, and the program will not receive any hardware interrupts until it executes an STI to reenable interrupts (or calls service 0901h).

When a protected-mode program executes a PUSHF instruction, the real processor flags will be pushed onto the stack. Thus, examining the flags pushed on the stack is not sufficient to determine the state of the program's virtual interrupt flag. These services enable programs to get and modify the state of their virtual interrupt flag.

The following sample code enters an interrupt critical section and then restores the virtual interrupt state to it's previous state.

```
; Disable interrupts and get previous interrupt state
;
    mov ax, 0900h
    int 31h
;
; At this point AX = 0900h or 0901h
;
    .
    .
; Restore previous state (assumes AX unchanged)
;
    int 31h
```

**Function 0900H** This function gets and disables Virtual Interrupt State. This function will disable the virtual interrupt flag and return the previous state of the virtual interrupt flag. Pass the following information:

#### AX = 0900H

After the call, the carry flag is clear (this function always succeeds) and virtual interrupts are disabled.

AL = 0 if virtual interrupts were previously disabled. AL = 1 if virtual interrupts were previously enabled.

#### Notes:

1. AH will not be changed by this procedure. Therefore, to restore the previous state, simply execute an Int 31h.

**Function 0901H** This function gets and enables the Virtual Interrupt State. This function will enable the virtual interrupt flag and return the previous state of the virtual interrupt flag. Pass the following information:

#### AX = 0901H

After the call, the carry flag is clear (this function always succeeds) and virtual interrupts are enabled.

AL = 0 if virtual interrupts were previously disabled. AL = 1 if virtual interrupts were previously enabled.

#### Notes:

1. AH will not be changed by this procedure. Therefore, to restore the previous state, simply execute an Int 31h.

**Function 0902H** This function gets the Virtual Interrupt State. This function will return the current state of the virtual interrupt flag. Pass the following information:

#### AX = 0902H

After the call, the carry flag is clear (this function always succeeds).

AL = 0 if virtual interrupts are disabled.

AL = 1 if virtual interrupts are enabled.

### 11.2.11 Vendor Specific Extensions

Some DOS extenders provide extensions to the standard set of DPMI calls. This call is used to obtain an address which must be called to use the extensions. The caller points DS:ESI to a null terminated string that specifies the vendor name or some other unique identifier to obtain the specific extension entry point.

Function 0A00H This function gets Tenberry Software's API Entry Point. Pass the following information:

#### AX = 0A00H

#### DS:ESI = Pointer to null terminated string "RATIONAL DOS/4G"

If the call succeeds, the carry flag is clear and ES:EDI = Extended API entry point. DS, FS, GS, EAX, EBX, ECX, EDX, ESI, and EBP may be modified.

If the call fails, the carry flag is set.

#### Notes:

- 1. Execute a far call to call the API entry point.
- 2. All extended API parameters are specified by the vendor.
- 3. The string comparison used to return the API entry point is case sensitive.

## 11.2.12 Coprocessor Status

Function 0E00H This function gets the coprocessor status. Pass the following information:

#### AX = 0E00H

If the call succeeds, the carry flag is clear and AX contains the coprocessor status.

Bit	Significance
0	MPv (MP bit in the virtual MSW/CR0).
	0 = Numeric coprocessor is disabled for this client.
	1 = Numeric coprocessor is disabled for this client.
1	EMv (EM bit in the virtual MSW/CR0).
	0 = Client is not emulating coprocessor instructions.
	1 = Client is emulating coprocessor instructions.
2	MPr (MP bit from the actual MSW/CR0).
	0 = Numeric coprocessor is not present.
	1 = Numeric coprocessor is present.

1 EMr (EM bit from the actual MSW/CR0).

0 = Host is not emulating coprocessor instructions.

1 = Host is emulating coprocessor instructions.

*4-7* Coprocessor type.

00H = no coprocessor.

02H = 80287

03H = 80387

04H = 80486 with numeric coprocessor

05H = Pentium

8-15 Not applicable.

If the call fails, the carry flag is set.

#### Notes:

- 1. If the real EM (EMr) bit is set, the host is supplying or is capable of supplying floating-point emulation.
- 2. If the MPv bit is not set, the host may not need to save the coprocessor state for this virtual machine to improve system performance.
- 3. The MPr bit setting should be consistent with the setting of the coprocessor type information. Ignore MPr bit information if it is in conflict with the coprocessor type information.
- 4. If the virtual EM (EMv) bit is set, the host delivers all coprocessor exceptions to the client, and the client is performing its own floating-point emulation (wether or not a coprocessor is present or the host also has a floating-point emulator). In other words, if the EMv bit is set, the host sets the EM bit in the real CR0 while the virtual machine is active, and reflects coprocessor not present faults (int 7) to the virtual machine.
- 5. A client can determine the CPU type with int 31H Function 0400H, but a client should not draw any conclusions about the presence or absence of a coprocessor based on the CPU type alone.

Function 0E01H This function sets coprocessor emulation. Pass the following information:

AX = 0E01H BX = coprocessor bits

Bit	Significance
0	New value of MPv bit for client's virtual CR0.
	0 = Disable numeric coprocessor for this client.
	1 = Enable numeric coprocessor for this client.
1	New value of EMv bit for client's virtual CR0.
	0 = client will not supply coprocessor emulation.
	1 = client will supply coprocessor emulation.
2-15	Not applicable.

If the call succeeds, the carry flag is clear; if it fails, the carry flag is set.

# 12 Utilities

This chapter describes the Tenberry Software *DOS/4GW* utility programs provided with the Open Watcom C/C++ package. Each program is described using the following format:

**Purpose:** This is a brief statement of what the utility program does. More specific information is provided under "Notes".

**Syntax:** This shows the syntax of the program. The fixed portion of each command is in a typewriter font, while variable parts of the command are in *italics*. Optional parts are enclosed in [brackets].

**Notes:** These are explanatory remarks noting major features and possible pitfalls. We explain anything special that you might need to know about the program.

See Also: This is a cross-reference to any information that is related to the program.

**Example:** You'll find one or more sample uses of the utility program with an explanation of what the program is doing.

Some of the utilities are *DOS/4GW*-based, protected-mode programs. To determine which programs run in protected mode and which in real, run the program. If you see the *DOS/4GW* banner, the program runs in protected mode.

# 12.1 DOS4GW

Purpose: Loads and executes linear executables.

Syntax: linear\_executable

Notes: The stub program at the beginning of the linear executable invokes this program, which loads the

linear executable and starts up the DOS extender. The stub program must be able to find

DOS4GW: make sure it is in the path.

### 12.2 PMINFO

**Purpose:** Measures the performance of protected/real-mode switching and extended memory.

Syntax: PMINFO.EXE

**Notes:** We encourage you to distribute this program to your users.

The time-based measurements made by PMINFO may vary slightly from run to run.

*Example:* The following example shows the output of the PMINFO program on a 386 AT-compatible machine.

```
C>pminfo
     Protected Mode and Extended Memory Performance Measurement -- 5.00
             Copyright (c) Tenberry Software, Inc. 1987 - 1993
DOS memory
            Extended memory
                               CPU performance equivalent to 67.0 MHz 80486
       736
                        8012
                               K bytes configured (according to BIOS).
       640
                       15360
                               K bytes physically present (SETUP).
       651
                        7887
                               K bytes available for DOS/16M programs.
22.0 (3.0)
                  18.9 (4.0)
                               MB/sec word transfer rate (wait states).
42.9 (3.0)
                  37.0 (4.0)
                              MB/sec 32-bit transfer rate (wait states).
Overall cpu and memory performance (non-floating point) for typical
DOS programs is 10.36 æ 1.04 times an 8MHz IBM PC/AT.
Protected/Real switch rate = 36156/sec (27 usec/switch, 15 up + 11 down),
DOS/16M switch mode 11 (VCPI).
```

The top information line shows that the CPU performance is equivalent to a 67.0 MHz 80486. Below are the configuration and timings for both the DOS memory and extended memory. If the computer is not equipped with extended memory, or none is available for *DOS/4GW*, the extended memory measurements may be omitted ("--").

The line "according to BIOS" shows the information provided by the BIOS (interrupts 12h and 15h function 88h). The line "SETUP", if displayed, is the configuration obtained directly from the CMOS RAM as set by the computer's setup program. It is displayed only if the numbers are different from those in the BIOS line. They will be different for computers where the BIOS has reserved memory for itself or if another program has allocated some memory and is intercepting the BIOS configuration requests to report less memory available than is physically configured. The "DOS/16M memory range", if displayed, shows the low and high addresses available to DOS/4GW in extended memory.

Below the configuration information is information on the memory speed (*transfer rate*). PMINFO tries to determine the memory architecture. Some architectures will perform well under some circumstances and poorly under others; PMINFO will show both the best and worst cases. The architectures detected are cache, interleaved, page-mode (or static column), and direct. Measurements are made using 32-bit accesses and reported as the number of megabytes per second that can be transferred. The number of wait states is reported in parentheses. The wait states can be a fractional number, like 0.5, if there is a wait state on writes but not on reads. Memory bandwidth (i.e., how fast the CPU can access memory) accounts for 60% to 70% of the performance for typical programs (that are not heavily dependent on floating-point math).

### The DOS/4GW DOS Extender

A performance metric developed by Tenberry Software is displayed, showing the expected throughput for the computer relative to a standard 8MHz IBM PC/AT (disk accesses and floating point are excluded). Finally, the speed with which the computer can switch between real and protected mode is displayed, both as the maximum number of round-trip switches that can occur per second, and the time for a single round-trip switch, broken out into the real-to-protected (up) and protected-to-real (down) components.

### 12.3 PRIVATXM

**Purpose:** Creates a private pool of memory for DOS/4GW programs.

Syntax: PRIVATXM [-r]

**Notes:** This program may be distributed to your users.

Without PRIVATXM, a *DOS/4GW* program that starts up while another *DOS/4GW* program is active uses the pool of memory built by the first program. The new program cannot change the parameters of this memory pool, so setting **DOS16M** to increase the size of the pool has no effect. To specify that the two programs use different pools of memory, use PRIVATXM.

PRIVATXM marks the active *DOS/4GW* programs as private, preventing subsequent *DOS/4GW* programs from using the same memory pool. The first *DOS/4GW* program to start after PRIVATXM sets up a new pool of memory for itself and any subsequent *DOS/4GW* programs. To release the memory used by the private programs, use the PRIVATXM -r option.

PRIVATXM is a TSR that requires less than 500 bytes of memory. It is not supported under DPMI.

*Example:* The following example creates a 512KB memory pool that is shared by two *DOS/4GW* TSRs. Subsequent *DOS/4GW* programs use a different memory pool.

*C>set DOS16M=:512* Specifies the size of the memory pool.

*C>TSR1* Sets up the memory pool at startup.

*C>TSR2* This TSR shares the pool built by TSR1.

**C>PRIVATXM** Makes subsequent *DOS/4GW* programs use a new memory pool.

*C>set DOS16M*= Specifies an unlimited size for the new pool.

*C>PROGRAM3* This program uses the new memory pool.

*C>PRIVATXM -R* Releases the 512KB memory pool used by the TSRs. (If the TSRs

shut down, their memory is not released unless PRIVATXM is

released.)

### 12.4 RMINFO

**Purpose:** Supplies configuration information and the basis for real/protected-mode switching in your

machine.

Syntax: RMINFO.EXE

*Notes:* This program may be distributed to your users.

RMINFO starts up *DOS/4GW*, but stops your machine just short of switching from real mode to protected mode and displays configuration information about your computer. The information shown by RMINFO can help determine why *DOS/4GW* applications won't run on a particular machine. Run RMINFO if PMINFO does not run to completion.

*Example:* The following example shows the output of the RMINFO program on an 386 AT-compatible machine.

```
C>rminfo
DOS/16M Real Mode Information Program 5.00
Copyright (C) Tenberry Software, Inc. 1987 - 1993
Machine and Environment:

Processor:
Machine type:
A20 now:
A20 switch rigor:
Date bost found

i386, coprocessor present
10 (AT-compatible)
enabled
disabled
Switching Functions:
                                         DPMI
          To PM switch:
          To RM switch:
                                         DPMI
          Nominal switch mode:
                                         0
          Switch control flags:
                                         0000
Memory Interfaces:
                                         16384K returnable
          DPMI may provide:
          Contiguous DOS memory: 463K
```

The information provided by RMINFO includes:

#### Machine and Environment:

**Processor:** processor type, coprocessor present/not present

Machine type:

```
(NEC 9801)
                    (PS/2-compatible)
                    (AT-compatible)
                    (FMR)
                    (AT&T 6300+)
                    (AT-compatible)
                    (C&T 230 chipset)
                    (AT-compatible)
                    (AT-compatible)
                    (Acer)
                    (Zenith)
                    (Hitachi)
                    (Okidata)
                    (PS/55)
               Current state of Address line 20.
A20 switch rigor: Whether DOS4GW rigorously controls enabling and disabling of Address line
               20 when switching modes.
XMS host found Whether your system has any software using extended memory under the XMS
               discipline.
VCPI host found Whether your system has any software using extended memory under the
               VCPI discipline.
page table 0 at: x000h
DOS/16M resident with private/public memory
Switching Functions:
To PM switch: reset catch:
               pre-PM prep:
               post-PM-switch:
               pre-RM prep:
               reset method:
               post-reset:
               reset uncatch:
```

A20 now:

PS feature flag

DPMI host found

A20 switching:

To RM switch:

Nominal switch mode: x

Switch control flags: xxxxh

### The DOS/4GW DOS Extender

Memory Interfaces:

(VCPI remapping in effect)

DPMI may provide: xxxxXK returnable

VCPI may provide: xxxxxK returnable

Top-down

Other16M

**Forced** 

Contiguous DOS memory:

# 13 Error Messages

The following lists DOS/4G error messages, with descriptions of the circumstances in which the error is most likely to occur, and suggestions for remedying the problem. Some error messages pertaining to features — like DLLs — that are not supported in *DOS/4GW* will not arise with that product. In the following descriptions, references to DOS/4G, DOS4G, or DOS4G.EXE may be replaced by DOS/4GW, DOS4GW, or DOS4GW.EXE should the error message arise when using *DOS/4GW*.

# 13.1 Kernel Error Messages

This section describes error messages from the DOS/16M kernel embedded in DOS/4G. Kernel error messages may occur because of severe resource shortages, corruption of DOS4GW.EXE, corruption of memory, operating system incompatibilities, or internal errors in DOS/4GW. All of these messages are quite rare.

#### 0. involuntary switch to real mode

The computer was in protected mode but switched to real mode without going through DOS/16M. This error most often occurs because of an unrecoverable stack segment exception (stack overflow), but can also occur if the Global Descriptor Table or Interrupt Descriptor Table is corrupted. Increase the stack size, recompile your program with stack overflow checking, or look into ways that the descriptor tables may have been overwritten.

#### 1. not enough extended memory

#### 2. not a DOS/16M executable <filename>

DOS4G.EXE, or a bound DOS/4G application, has probably been corrupted in some way. Rebuild or recopy the file.

- 3. no DOS memory for transparent segment
- 4. cannot make transparent segment
- 5. too many transparent segments
- 6. not enough memory to load program

There is not enough memory to load DOS/4G. Make more memory available and try again.

- 7. no relocation segment
- 8. cannot open file <filename>

The DOS/16M loader cannot load DOS/4G, probably because DOS has run out of file units. Set a larger FILES= entry in CONFIG.SYS, reboot, and try again.

#### 9. cannot allocate tstack

There is not enough memory to load DOS/4G. Make more memory available and try again.

#### 10. cannot allocate memory for GDT

There is not enough memory to load DOS/4G. Make more memory available and try again.

#### 11. no passup stack selectors -- GDT too small

This error indicates an internal error in DOS/4G or an incompatibility with other software.

#### 12. no control program selectors -- GDT too small

This error indicates an internal error in DOS/4G or an incompatibility with other software.

#### 13. cannot allocate transfer buffer

There is not enough memory to load DOS/4G. Make more memory available and try again.

#### 14. premature EOF

DOS4G.EXE, or a bound DOS/4G application, has probably been corrupted in some way. Rebuild or recopy the file.

#### 15. protected mode available only with 386 or 486

DOS/4G requires an 80386 (or later) CPU. It cannot run on an 80286 or earlier CPU.

#### 16. cannot run under OS/2

#### 17. system software does not follow VCPI or DPMI specifications

Some memory resident program has put your 386 or 486 CPU into Virtual 8086 mode. This is done to provide special memory services to DOS programs, such as EMS simulation (EMS interface without EMS hardware) or high memory. In this mode, it is not possible to switch into protected mode unless the resident software follows a standard that DOS/16M supports (DPMI, VCPI, and XMS are the most common). Contact the vendor of your memory management software.

#### 18. you must specify an extended memory range (SET DOS16M=)

On some Japanese machines that are not IBM AT-compatible, and have no protocol for managing extended memory, you must set the DOS16M environment variable to specify the range of available extended memory.

#### 19. computer must be AT- or PS/2- compatible

#### 20. unsupported DOS16M switchmode choice

#### 21. requires DOS 3.0 or later

#### 22. cannot free memory

This error probably indicates that memory was corrupted during execution of your program.

#### 23. no memory for VCPI page table

There is not enough memory to load DOS/4G. Make more memory available and try again.

#### 24. VCPI page table address incorrect

This is an internal error.

#### 25. cannot initialize VCPI

This error indicates an incompatibility with other software. DOS/16M has detected that VCPI is present, but VCPI returns an error when DOS/16M tries to initialize the interface.

#### 26, 8042 timeout

#### 27. extended memory is configured but it cannot be allocated

#### 28. memory error, avail loop

This error probably indicates that memory was corrupted during execution of your program. Using an invalid or stale alias selector may cause this error. Incorrect manipulation of segment descriptors may also cause it.

#### 29. memory error, out of range

This error probably indicates that memory was corrupted during execution of your program. Writing through an invalid or stale alias selector may cause this error.

#### 30. program must be built -AUTO for DPMI

- 31. protected mode already in use in this DPMI virtual machine
- 32. DPMI host error (possibly insufficient memory)
- 33. DPMI host error (need 64K XMS)
- 34. DPMI host error (cannot lock stack)

Any of these errors (32, 33, 34) probably indicate insufficient memory under DPMI. Under Windows, you might try making more physical memory available by eliminating or reducing any RAM drives or disk caches. You might also try editing DEFAULT.PIF so that at least 64KB of XMS memory is available to non-Windows programs. Under OS/2, you want to increase the DPMI\_MEMORY\_LIMIT in the DOS box settings.

#### 35. General Protection Fault

This message probably indicates an internal error in DOS/4G. Faults generated by your program should cause error 2001 instead.

#### 36. The DOS16M.386 virtual device driver was never loaded

#### 37. Unable to reserve selectors for DOS16M.386 Windows driver

#### 38. Cannot use extended memory: HIMEM.SYS not version 2

This error indicates an incompatibility with an old version of HIMEM.SYS.

#### 39. An obsolete version of DOS16M.386 was loaded

#### 40. not enough available extended memory (XMIN)

This message probably indicates an incompatibility with your memory manager or its configuration. Try configuring the memory manager to provide more extended memory, or change memory managers.

### 13.2 DOS/4G Errors

#### 1000 "can't hook interrupts"

A DPMI host has prevented DOS/4G from loading. Please contact Tenberry Technical Support.

#### 1001 "error in interrupt chain"

DOS/4G internal error. Please contact Tenberry Technical Support.

#### 1003 "can't lock extender kernel in memory"

DOS/4G couldn't lock the kernel in physical memory, probably because of a memory shortage.

#### 1004 "syntax is DOS4G <executable.xxx>"

You must specify a program name.

#### 1005 "not enough memory for dispatcher data"

There is not enough memory for DOS/4G to manage user-installed interrupt handlers properly. Free some memory for the DOS/4G application.

#### 

DOS/4G could not open the specified program. Probably the file didn't exist. It is possible that DOS ran out of file handles, or that a network or similar utility has prohibited read access to the program. Make sure that the file name was spelled correctly.

#### 1008 "can't load executable format for file <filename> [<error code>]"

DOS/4G did not recognize the specified file as a valid executable file. DOS/4G can load linear executables (LE and LX) and EXPs (BW). The error code is for Tenberry Software's use.

#### 1009 "program <filename> is not bound"

This message does not occur in DOS/4G, only DOS/4GW Professional; the latter requires that the DOS extender be bound to the program file. The error signals an attempt to load

#### 1010 "can't initialize loader <loader> [<error code>]"

DOS/4G could not initialize the named loader, probably because of a resource shortage. Try making more memory available. If that doesn't work, please contact Tenberry Technical Support. The error code is for Tenberry Software' use.

#### 1011 "VMM initialization error [<error code>]"

DOS/4G could not initialize the Virtual Memory Manager, probably because of a resource shortage. Try making more memory available. If that doesn't work, please contact Tenberry Technical Support. The error code is for Tenberry Software' use.

#### 1012 "<filename> is not a WATCOM program"

This message does not occur in DOS/4G, only DOS/4GW and DOS/4GW Professional. Those extenders only support WATCOM 32-bit compilers.

#### 1013 "int 31h initialization error"

DOS/4G was unable to initialize the code that handles Interrupt 31h, probably because of an internal error. Please call Tenberry Technical Support.

#### 1100 "assertion \"<statement>\" failed (<file>:<line>)"

DOS/4G internal error. Please contact Tenberry Technical Support.

#### 1200 "invalid EXP executable format"

DOS/4G tried to load an EXP, but couldn't. The executable file is probably corrupted.

#### 1201 "program must be built -AUTO for DPMI"

Under DPMI, DOS/4G can only load EXPs that have been linked with the GLU -AUTO or -DPMI switch.

#### 1202 "can't allocate memory for GDT"

There is not enough memory available for DOS/4G to build a Global Descriptor Table. Make more memory available.

#### 1203 "premature EOF"

DOS/4G tried to load an EXP but couldn't. The file is probably corrupted.

#### 1204 "not enough memory to load program"

There is not enough memory available for DOS/4G to load your program. Make more memory available.

#### 1301 "invalid linear executable format"

DOS/4G cannot recognize the program file as a LINEXE format. Make sure that you specified the correct file name.

#### 1304 "file I/O seek error"

DOS/4G was unable to seek to a file location that should exist. This usually indicates truncated program files or problems with the storage device from which your program loads. Run CHKDSK or a similar utility to begin determining possible causes.

#### 1305 "file I/O read error"

DOS/4G was unable to read a file location that should contain program data. This usually indicates truncated program files or problems with the storage device from which your program loads. Run CHKDSK or a similar utility to begin determining possible causes.

#### 1307 "not enough memory"

As it attempted to load your program, DOS/4G ran out of memory. Make more memory available, or enable VMM.

1308 "can't load requested program"

1309 "can't load requested program"

1311 "can't load requested program"

#### 1312 "can't load requested program"

DOS/4G cannot load your program for some reason. Contact Tenberry Technical Support.

#### 1313 "can't resolve external references"

DOS/4G was unable to resolve all references to DLLs for the requested program, or the program contained unsupported fixup types. Use EXEHDR or a similar LINEXE dump utility to see what references your program makes and what special fixup records might be present.

#### 1314 "not enough lockable memory"

As it attempted to load your program, DOS/4G encountered a refusal to lock a virtual memory region. Some memory must be locked in order to handle demand-load page faults. Make more physical memory available.

#### 1315 "can't load requested program"

#### 1316 "can't load requested program"

DOS/4G cannot load your program for some reason. Contact Tenberry Technical Support.

#### 1317 "program has no stack"

DOS/4G reports this error when you try to run a program with no stack. Rebuild your program, building in a stack.

#### 2000 "deinitializing twice"

DOS/4G internal error. Please contact Tenberry Technical Support.

2001 "exception <exception\_number> (<exception\_description>) at <selector:offset>"

Your program has generated an exception. For information about interpreting this message, see the file COMMON.DOC.

#### 2002 "transfer stack overflow at <selector:offset>"

Your program has overflowed the DOS/4G transfer stack. For information about interpreting this message, see the file COMMON.DOC.

#### 2300 " can't find <DLL>.<ordinal> - referenced from <module>"

DOS/4G could not find the ordinal listed in the specified DLL, or it could not find the DLL at all. Correct or remove the reference, and make sure that DOS/4G can find the DLL.

DOS/4G looks for DLLs in the following directories:

- The directory specified by the Libpath32 configuration option (which defaults to the directory of the main application file).
- The directory or directories specified by the LIBPATH32 environment variable.
- Directories specified in the PATH.

#### 2301 "can't find <DLL>.<name> - referenced from <module>"

DOS/4G could not find the entry point named in the specified module. Correct or remove the reference, and make sure that DOS/4G can find the DLL.

#### 2302 "DLL modules not supported"

This DOS/4GW Professional error message arises when an application references or tries to explicitly load a DLL. DOS/4GW Professional does not support DLLs.

#### 2303 "internal LINEXE object limit reached"

DOS/4G currently handles a maximum of 128 LINEXE objects, including all .DLL and .EXE files. Most .EXE or .DLL files use only three or four objects. If possible, reduce the number of objects, or contact Tenberry Technical Support.

#### 2500 "can't connect to extender kernel"

DOS/4G internal error. Please contact Tenberry Technical Support.

#### 2503 "not enough disk space for swapping - <count> byes required"

VMM was unable to create a swap file of the required size. Increase the amount of disk space available.

#### 2504 "can't create swap file \<filename>\""

VMM was unable to create the swap file. This could be because the swap file is specified for a nonexistent drive or on a drive that is read-only. Set the SWAPNAME parameter to change the location of the swap file.

#### 2505 "not enough memory for "

VMM was unable to get sufficient extended memory for internal tables. Make more memory available. If is page buffer, make more DOS memory available.

#### 2506 "not enough physical memory (minmem)"

There is less physical memory available than the amount specified by the MINMEM parameter. Make more memory available.

#### 2511 "swap out error [<error code>]"

Unknown disk error. The error code is for Tenberry Software' use.

#### 2512 "swap in error [<error code>]"

Unknown disk error. The error code is for Tenberry Software' use.

#### 2514 "can't open trace file"

VMM could not open the VMM.TRC file in the current directory for writing. If the directory already has a VMM.TRC file, delete it. If not, there may not be enough memory on the drive for the trace file, or DOS may not have any more file handles.

#### 2520 "can't hook int 31h"

DOS/4G internal error. Please contact Tenberry Technical Support.

#### 2523 "page fault on non-present mapped page"

Your program references memory that has been mapped to a nonexistent physical device, using DPMI function 508h. Make sure the device is present, or remove the reference.

#### 2524 "page fault on uncommitted page"

Your program references memory reserved with a call to DPMI function

### 504h, but never committed (using a DPMI 507h or 508h call). Commit the memory before you reference it.

#### 3301 "unhandled EMPTYFWD, GATE16, or unknown relocation"

#### 3302 "unhandled ALIAS16 reference to unaliased object"

#### 3304 "unhandled or unknown relocation"

If your program was built for another platform that supports the LINEXE format, it may contain a construct that DOS/4G does not currently support, such as a call gate. This message may also occur if your program has a problem mixing 16- and 32-bit code. A linker error is another likely cause.

# 14 DOS/4GW Commonly Asked Questions

The following information has been provided by Tenberry Software, Inc. for their DOS/4GW and DOS/4GW Professional product. The content of this chapter has been edited by Open Watcom. In most cases, the information is applicable to both products.

This chapter covers the following topics:

- Access to technical support
- Differences within the DOS/4G product line
- Addressing
- Interrupt and exception handling
- Memory management
- DOS, BIOS, and mouse services
- Virtual memory
- Debugging
- Compatibility

### 14.1 Access to Technical Support

1a. How to reach technical support.

Here are the various ways you may contact Tenberry Software for technical support.

```
WWW:
       http://www.tenberry.com/dos4g/
Email: 4gwhelp@tenberry.com
Phone: 1.480.767.8868
Fax:
       1.480.767.8709
Mail: Tenberry Software, Inc.
       PO Box 20050
        Fountain Hills, Arizona
```

U.S.A 85269-0050

PLEASE GIVE YOUR SERIAL NUMBER WHEN YOU CONTACT TENBERRY.

#### 1b. When to contact Open Watcom, when to contact Tenberry.

Since DOS/4GW Professional is intended to be completely compatible with DOS/4GW, you may wish to ascertain whether your program works properly under DOS/4GW before contacting Tenberry Software for technical support. (This is likely to be the second question we ask you, after your serial number.)

If your program fails under both DOS/4GW and DOS/4GW Professional, and you suspect your own code or a problem compiling or linking, you may wish to contact Open Watcom first. Tenberry Software support personnel are not able to help you with most programming questions, or questions about using the Open Watcom tools.

If your program only fails with DOS/4GW Professional, you have probably found a bug in DOS/4GW Professional, so please contact us right away.

#### 1c. Telephone support.

Tenberry Software's hours for telephone support are 9am-6pm EST. Please note that telephone support is free for the first 30 days only. A one-year contract for continuing telephone support on DOS/4GW Professional is US\$500 per developer, including an update subscription for one year, to customers in the United States and Canada; for overseas customers, the price is \$600. Site licenses may be negotiated.

There is no time limit on free support by fax, mail, or electronic means.

#### 1d. References.

The DOS/4GW documentation from Open Watcom is the primary reference for DOS/4GW Professional as well. Another useful reference is the DPMI specification. In the past, the DPMI specification could be obtained free of charge by contacting Intel Literature. We have been advised that the DPMI specification is no longer available in printed form.

However, the DPMI 1.0 specification can be obtained at:

http://www.delorie.com/djgpp/doc/dpmi/

Online HTML as well as a downloadable archive are provided.

### 14.2 Differences Within the DOS/4G Product Line

#### 2a. DOS/4GW Professional versus DOS/4GW

DOS/4GW Professional was designed to be a higher-performance version of DOS/4GW suitable for commercial applications. Here is a summary of the advantages of DOS/4GW Professional with respect to DOS/4GW:

- Extender binds to the application program file
- Extender startup time has been reduced
- Support for Open Watcom floating-point emulator has been optimized
- Virtual memory manager performance has been greatly improved

- Under VMM, programs are demand loaded
- Virtual address space is 4 GB instead of 32 MB
- Extender memory requirements have been reduced by more than 50K
- Extender disk space requirements have been reduced by 40K
- Can omit virtual memory manager to save 50K more disk space
- Support for INT 31h functions 301h-304h and 702h-703h

DOS/4GW Professional is intended to be fully compatible with programs written for DOS/4GW 1.9 and up. The only functional difference is that the extender is bound to your program instead of residing in a separate file. Not only does this help reduce startup time, but it eliminates version-control problems when someone has both DOS/4GW and DOS/4GW Professional applications present on one machine.

#### 2b. DOS/4GW Professional versus DOS/4G.

DOS/4GW Professional is not intended to provide any other new DOS extender functionality. Tenberry Software's top-of-the-line 32-bit extender, DOS/4G, is not sold on a retail basis but is of special interest to developers who require more flexibility (such as OEMs). DOS/4G offers these additional features beyond DOS/4GW and DOS/4GW Professional:

- Complete documentation
- DLL support
- TSR support
- Support for INT 31h functions 301h-306h, 504h-50Ah, 702h-703h
- A C language API that offers more control over interrupt handling and program loading, as well as making it easier to use the extender
- An optional (more protected) nonzero-based flat memory model
- Remappable error messages
- More configuration options
- The D32 debugger, GLU linker, and other tools
- Support for other compilers besides Open Watcom
- A higher level of technical support
- Custom work is available (e.g., support for additional executable formats, operating system API emulations, mixed 16-bit and 32-bit code)

Please contact Tenberry Software if you have questions about other products (present or future) in the DOS/4G line.

#### 2c. DPMI functions supported by DOS/4GW.

Note that when a DOS/4GW application runs under a DPMI host, such as Windows 3.1 in enhanced mode, an OS/2 virtual DOS machine, 386Max (with DEBUG=DPMIXCOPY), or QDPMI (with EXTCHKOFF), the DPMI host provides the DPMI services, not DOS/4GW. The DPMI host also provides virtual memory, if any. Performance (speed and memory use) under different DPMI hosts varies greatly due to the quality of the DPMI implementation.

These are the services provided by DOS/4GW and DOS/4GW Professional in the absence of a DPMI host.

0000	All LDTD
0000	Allocate LDT Descriptors
0001 0002	Free LDT Descriptor  Man Book Mode Segment to Descriptor
0002	Map Real-Mode Segment to Descriptor Get Selector Increment Value
0006	Get Segment Base Address
0007	Set Segment Base Address
0008	Set Segment Limit
0009	Set Descriptor Access Rights
000A	Create Alias Descriptor
000B	Get Descriptor
000C	Set Descriptor
000D	Allocate Specific LDT Descriptor
0100	Allocate DOS Memory Block
0101	Free DOS Memory Block
0102	Resize DOS Memory Block
0200	Get Real-Mode Interrupt Vector
0201	Set Real-Mode Interrupt Vector
0202	Get Processor Exception Handler
0203	Set Processor Exception Handler
0204	Get Protected-Mode Interrupt Vector
0205	Set Protected-Mode Interrupt Vector
0300	Simulate Real-Mode Interrupt
0301	Call Real-Mode Procedure with Far Return Frame (DOS/4GW Professional only)
0302	Call Real-Mode Procedure with IRET Frame (DOS/4GW Professional only)
0302	Allocate Real-Mode Callback Address (DOS/4GW Professional only)
0304	Free Real-Mode Callback Address (DOS/4GW Professional only)
0304	The Real Mode Callback Address (Book-to W Trolessional only)
0400	Get DPMI Version
0500	Get Free Memory Information
0501	Allocate Memory Block
0502	Free Memory Block
0502 0503	Resize Memory Block
0303	Resize Memory Block
0600	Lock Linear Region
0601	Unlock Linear Region
0604	Get Page Size (VM only)
0702	Mark Page as Demand Paging Candidate (DOS/4GW Professional only)
0/02	Mark 1 age as Demand 1 aging Candidate (DOS/40 W F1016551011at Oilly)

Discard Page Contents (DOS/4GW Professional only)
Physical Address Mapping
Free Physical Address Mapping
Get and Disable Virtual Interrupt State
Get and Enable Virtual Interrupt State
Get Virtual Interrupt State
Get Tenberry Software API Entry Point
Get Coprocessor Status
Set Coprocessor Emulation

### 14.3 Addressing

#### 3a. Converting between pointers and linear addresses.

Because DOS/4GW uses a zero-based flat memory model, converting between pointers and linear addresses is trivial. A pointer value is always relative to the current segment (the value in CS for a code pointer, or in DS or SS for a data pointer). The segment bases for the default DS, SS, and CS are all zero. Hence a near pointer is exactly the same thing as a linear address: a null pointer points to linear address 0, and a pointer with value 0x10000 points to linear address 0x10000.

#### 3b. Converting between code and data pointers.

Because DS and CS have the same base address, they are natural aliases for each other. To create a data alias for a code pointer, merely create a data pointer and set it equal to the code pointer. It's not necessary for you to create your own alias descriptor. Similarly, to create a code alias for a data pointer, merely create a code pointer and set it equal to the data pointer.

#### 3c. Converting between pointers and low memory addresses.

Linear addresses under 1 MB map directly to physical memory. Hence the real-mode interrupt vector table is at address 0, the BIOS data segment is at address 0x400, the monochrome video memory is at address 0xB0000, and the color video memory is at address 0xB8000. To read and write any of these, you can just use a pointer set to the proper address. You don't need to create a far pointer, using some magic segment value.

#### 3d. Converting between linear and physical addresses.

Linear addresses at or above 1 MB do not map directly to physical memory, so you can not in general read or write extended memory directly, nor can you tell how a particular block of extended memory has been used.

DOS/4GW supports the DPMI call INT 31h/800h, which maps physical addresses to linear addresses. In other words, if you have a peripheral device in your machine that has memory at a physical address of 256 MB, you can issue this call to create a linear address that points to that physical memory. The linear address is the same thing as a near pointer to the memory and can be manipulated as such.

There is no way in a DPMI environment to determine the physical address corresponding to a given linear address. This is part of the design of DPMI. You must design your application accordingly.

#### 3e. Null pointer checking.

DOS/4GW will trap references to the first sixteen bytes of physical memory if you set the environment variable DOS4G=NULLP. This is currently the only null-pointer check facility provided by DOS/4GW.

As of release 1.95, DOS/4GW traps both reads and writes. Prior to this, it only trapped writes.

You may experience problems if you set DOS4G=NULLP and use some versions of the Open Watcom Debugger with a 1.95 or later extender. These problems have been corrected in later versions of the Open Watcom Debugger.

### 14.4 Interrupt and Exception Handling

#### 4a. Handling asynchronous interrupts.

Under DOS/4GW, there is a convenient way to handle asynchronous interrupts and an efficient way to handle them.

Because your CPU may be in either protected mode (when 32-bit code is executing) or real mode (a DOS or BIOS call) when a hardware interrupt comes in, you have to be prepared to handle interrupts in either mode. Otherwise, you may miss interrupts.

You can handle both real-mode and protected-mode interrupts with a single handler, if 1) the interrupt is in the auto-passup range, 8 to 2Eh; and 2) you install a handler with INT 21h/25h or \_dos\_setvect(); 3) you do not install a handler for the same interrupt using any other mechanism. DOS/4GW will route both protected-mode interrupts and real-mode interrupts to your protected-mode handler. This is the convenient way.

The efficient way is to install separate real-mode and protected-mode handlers for your interrupt, so your CPU won't need to do unnecessary mode switches. Writing a real-mode handler is tricky; all you can reasonably expect to do is save data in a buffer and IRET. Your protected-mode code can periodically check the buffer and process any queued data. (Remember, protected-mode code can access data and execute code in low memory, but real-mode code can't access data or execute code in extended memory.)

For performance, it doesn't matter how you install the real-mode handler, but we recommend the DPMI function INT 31h/201h for portability.

It does matter how you install the protected-mode handler. You can't install it directly into the IDT, because a DPMI provider must distinguish between interrupts and exceptions and maintain separate handler chains. Installing with INT 31h/205h is the recommended way to install your protected-mode handler for both performance and portability.

If you install a protected-mode handler with INT 21h/25h, both interrupts and exceptions will be funneled to your handler, to mimic DOS. Since DPMI exception handlers and interrupt handlers are called with different stack frames, DOS/4GW executes a layer of code to cover these differences up; the same layer is used to support the DOS/4G API (not part of DOS/4GW). This layer is the reason that hooking with INT 21h/25h is less efficient than hooking with INT 31h/205h.

#### 4b. Handling asynchronous interrupts in the second IRQ range.

Because the second IRQ range (normally INTs 70h-77h) is outside the DOS/4GW auto-passup range (8-2Eh, excluding 21h) you may not handle these interrupts with a single handler, as described above (the "convenient" method). You must install separate real-mode and protected-mode handlers (the "efficient" method).

DOS/4G does allow you to specify additional passup interrupts, however.

#### 4c. Asynchronous interrupt handlers and DPMI.

The DPMI specification requires that all code and data referenced by a hardware interrupt handler MUST be locked at interrupt time. A DPMI virtual memory manager can use the DOS file system to swap pages of memory to and from the disk; because DOS is not reentrant, a DPMI host is not required to be able to handle page faults during asynchronous interrupts. Use INT 31h/600h (Lock Linear Region) to lock an address range in memory.

If you fail to lock all of your code and data, your program may run under DOS/4GW, but fail under the DOS/4GW Virtual Memory Manager or under another DPMI host such as Windows or OS/2.

You should also lock the code and data of a mouse callback function.

#### 4d. Open Watcom signal() function and Ctrl-Break.

In earlier versions of the Open Watcom C/C++ library, there was a bug that caused signal(SIGBREAK) not to work. Calling signal(SIGBREAK) did not actually install an interrupt handler for Ctrl-Break (INT 1Bh), so Ctrl-Break would terminate the application rather than invoking the signal handler.

With these earlier versions of the library, you could work around this problem by hooking INT 1Bh directly. With release 10.0, this problem has been fixed.

#### 4e. More tips on writing hardware interrupt handlers.

• It's more like handling interrupts in real mode than not.

The same problems arise when writing hardware interrupt handlers for protected mode as arise for real mode. We assume you know how to write real-mode handlers; if our suggestions don't seem clear, you might want to brush up on real-mode interrupt programming.

• Minimize the amount of time spent in your interrupt handlers.

When your interrupt handlers are called, interrupts are disabled. This means that no other system tasks can be performed until you enable interrupts (an STI instruction) or until your handler returns. In general, it's a good idea to handle interrupts as quickly as possible.

 Minimize the amount of time spent in the DOS extender by installing separate real-mode and protected-mode handlers.

If you use a passup interrupt handler, so that interrupts received in real mode are resignalled in protected mode by the extender, your application has to switch from real mode to protected mode to real mode once per interrupt. Mode switching is a time-consuming process, and interrupts are disabled during a mode switch. Therefore, if you're concerned about performance, you should install separate handlers for real-mode and protected-mode interrupts, eliminating the mode switch.

• If you can't just set a flag and return, enable interrupts (STI).

Handlers that do more than just set a flag or store data in a buffer should re-enable interrupts as soon as it's safe to do so. In other words, save your registers on the stack, establish your addressing conventions, switch stacks if you're going to — and then enable interrupts (STI), to give priority to other hardware interrupts.

• If you enable interrupts (STI), you should disable interrupts (CLI).

Because some DPMI hosts virtualize the interrupt flag, if you do an STI in your handler, you should be sure to do a CLI before you return. (CLI, then switch back to the original stack if you switched away, then restore registers, then IRET.) If you don't do this, the IRET will not necessarily restore the previous interrupt flag state, and your program may crash. This is a difference from real-mode programming, and it tends to show up as a problem when you try running your program in a Windows or OS/2 DOS box for the first time (but not before).

Add a reentrancy check.

If your handler doesn't complete its work by the time the next interrupt is signalled, then interrupts can quickly nest to the point of overflowing the transfer stack. This is a design flaw in your program, not in the DOS extender; a real-mode DOS program can have exactly the same behavior. If you can conceive of a situation where your interrupt handler can be called again before the first instance returns, you need to code in a reentrancy check of some sort (before you switch stacks and enable interrupts (STI), obviously).

Remember that interrupts can take different amounts of time to execute on different machines; the CPU manufacturer, CPU speed, speed of memory accesses, and CMOS settings (e.g. "system BIOS shadowing") can all affect performance in subtle ways. We recommend you program defensively and always check for unexpected reentry, to avoid transfer stack overflows.

• Switch to your own stack.

Interrupt handlers are called on a stack that typically has only a small amount of stack available (512 bytes or less). If you need to use more stack than this, you have to switch to your own stack on entry into the handler, and switch back before returning.

If you want to use C run-time library functions, which are compiled for flat memory model (SS == DS, and the base of CS == the base of DS), you need to switch back to a stack in the flat data segment first.

Note that switching stacks by itself won't prevent transfer stack overflows of the kind described above.

### 14.5 Memory Management

5a. Using the realloc() function.

In versions of Open Watcom C/C++ prior to 9.5b, there was a bug in the library implementation of realloc() under DOS/4GW and DOS/4GW Professional. This bug was corrected by Open Watcom in the 9.5b release.

#### 5b. Using all of physical memory.

DOS/4GW Professional is currently limited to 64 MB of physical memory. We do not expect to be able to fix this problem for at least six months. If you need more than 64 MB of memory, you must use virtual memory.

### 14.6 DOS, BIOS, and Mouse Services

#### 6a. Speeding up file I/O.

The best way to speed up DOS file I/O in DOS/4GW is to write large blocks (up to 65535 bytes, or the largest number that will fit in a 16-bit int) at a time from a buffer in low memory. In this case, DOS/4GW has to copy the least amount of data and make the fewest number of DOS calls in order to process the I/O request.

Low memory is allocated through INT 31h/0100h, Allocate DOS Memory Block. You can convert the real-mode segment address returned by INT 31h/0100h to a pointer (suitable for passing to setvbuf()) by shifting it left four bits.

#### 6b. Spawning.

It is possible to spawn one DOS/4GW application from another. However, two copies of the DOS extender will be loaded into memory. DOS/4G supports loading of multiple programs atop a single extender, as well as DLLs.

#### 6c. Mouse callbacks.

DOS/4GW Professional now supports the INT 31h interface for managing real-mode callbacks. However, you don't need to bother with them for their single most important application: mouse callback functions. Just register your protected-mode mouse callback function as you would in real mode, by issuing INT 33h/0Ch with the event mask in CX and the function address in ES:EDX, and your function will work as expected.

Because a mouse callback function is called asynchronously, the same locking requirement exists for a mouse callback function as for a hardware interrupt handler. See (4c) above.

#### 6d. VESA support.

While DOS/4GW automatically handles most INT 10h functions so that you can you can issue them from protected mode, it does not translate the INT 10h VESA extensions. The workaround is to use INT 31h/300h (Simulate Real-Mode Interrupt).

### 14.7 Virtual Memory

#### 7a. Testing for the presence of VMM.

INT 31h/400h returns a value (BX, bit 2) that tells if virtual memory is available. Under a DPMI host such as Windows 3.1, this will be the host's virtual memory manager, not DOS/4GW's.

You can test for the presence of a DOS/4G-family DOS extender with INT 31h/0A00h, with a pointer to the null-terminated string "RATIONAL DOS/4G" in DS:ESI. If the function returns with carry clear, a DOS/4G-family extender is running.

#### 7b. Reserving memory for a spawned application.

If you spawn one DOS/4GW application from another, you should set the DELETESWAP configuration option (i.e., SET DOS4GVM=deleteswap) so that the two applications don't try to use the same swap file. You should also set the MAXMEM option low enough so that the parent application doesn't take all available physical memory; memory that's been reserved by the parent application is not available to the child application.

#### 7c. Instability under VMM.

A program that hooks hardware interrupts, and works fine without VMM but crashes sporadically with it, probably needs to lock the code and data for its hardware interrupt handlers down in memory. DOS/4GW does not support page faults during hardware interrupts, because DOS services may not be available at that time. See (4c) and (6c) above.

Memory can be locked down with INT 31h/600h (Lock Linear Region).

#### 7d. Running out of memory with a huge virtual address space.

Because DOS/4GW has to create page tables to describe your virtual address space, we recommend that you set your VIRTUALSIZE parameter just large enough to accommodate your program. If you set your VIRTUALSIZE to 4 GB, the physical memory occupied by the page tables will be 4 MB, and that memory will not be available to DOS/4GW.

#### 7e. Reducing the size of the swap file.

DOS/4GW will normally create a swap file equal to your VIRTUALSIZE setting, for efficiency. However, if you set the SWAPMIN parameter to a size (in KB), DOS/4GW will start with a swap file of that size, and will grow the swap file when it has to. The SWAPINC value (default 64 KB) controls the incremental size by which the swap file will grow.

#### 7f. Deleting the swap file.

The DELETESWAP option has two effects: telling DOS/4GW to delete the swap file when it exits, and causing DOS/4GW to provide a unique swap file name if an explicit SWAPNAME setting was not given.

DELETESWAP is required if one DOS/4GW application is to spawn another; see (7b) above.

#### 7g. Improving demand-load performance of large static arrays.

DOS/4GW demand-loading feature normally cuts the load time of a large program drastically. However, if your program has large amounts of global, zero-initialized data (storage class BSS), the Open Watcom startup code will explicitly zero it (version 9.5a or earlier). Because the zeroing operation touches every page of the data, the benefits of demand-loading are lost.

Demand loading can be made fast again by taking advantage of the fact that DOS/4GW automatically zeroes pages of BSS data as they are loaded. You can make this change yourself by inserting a few lines into the startup routine, assembling it (MASM 6.0 will work), and listing the modified object module first when you link your program.

Here are the changes for \watcom\src\startup\386\cstart3r.asm (startup module from the C/C++ 9.5 compiler, library using register calling conventions). You can modify the workaround easily for other Open Watcom compilers:

```
; cstart3r.asm, circa line 332
              . . .
                                                         ; end of _BSS segment (start of STACK)
              mov
                            ecx, offset DGROUP:_end
                                                       ; start of _BSS segment
                          edi,offset DGROUP:_edata
             mov
              ----; RSI OPTIMIZATION
             mov eax, edi ; minimize _BSS initialization loop or eax, OFFFh ; compute address of first page after inc eax ; start of _BSS cmp eax, ecx ; if _BSS extends onto that page, jae allzero ; then we can rely on the loader mov ecx, eax ; zeroing the remaining pages
allzero:
;-----; END RSI OPTIMIZATION
             sub ecx,edi ; calc # of bytes in _BSS segment
mov dl,cl ; save bottom 2 bits of count in edx
shr ecx,2 ; calc # of dwords
sub eax,eax ; zero the _BSS segment
rep stosd ; ...
mov cl,dl ; get bottom 2 bits of count
and cl,3 ; ...
                       cl,3
stosb
                                                      ; ...
              rep
```

Note that the 9.5b and later versions of the Open Watcom C library already contain this enhancement.

#### 7h. How should I configure VM for best performance?

Here are some recommendations for setting up the DOS/4GW virtual memory manager.

VIRTUALSIZE Set to no more than twice the total amount of memory (virtual and otherwise) your program requires. If your program has 16 MB of code and data, set to 32 MB. (There is only a small penalty for setting this value larger than you will need, but your program won't run if you set it too low.) See (7d) above.

**MINMEM** Set to the minimum hardware requirement for running your application. (If you require a 2 MB machine, set to 2048).

**MAXMEM** Set to the maximum amount of memory you want your application to use. If you don't spawn any other applications, set this large (e.g., 32000) to make sure you can use all available physical memory. If you do spawn, see (7b) above.

Don't use this if you want the best possible VM performance. The trade-off is that *SWAPMIN* DOS/4GW will create a swap file as big as your VIRTUALSIZE.

**SWAPINC** Don't use this if you want the best possible VM performance.

**DELETESWAP** DOS/4GW's VM will start up slightly slower if it has to create the swap file afresh each time. However, unless your swap file is very large, DELETESWAP is a reasonable choice; it may be required if you spawn another DOS/4GW program at the same time. See (7b) above.

### 14.8 Debugging

#### 8a. Attempting to debug a bound application.

You can't debug a bound application. The 4GWBIND utility (included with DOS/4GW Professional) will allow you to take apart a bound application so that you can debug it:

```
4GWBIND -U <boundapp.exe> <yourapp.exe>
```

#### 8b. Debugging with an old version of the Open Watcom debugger.

DOS/4GW supports versions 8.5 and up of the Open Watcom C, C++ and FORTRAN compilers. However, in order to debug your unbound application with a Open Watcom debugger, you must have version 9.5a or later of the debugger.

If you have an older version of the debugger, we strongly recommend that you contact Open Watcom to upgrade your compiler and tools. The only way to debug a DOS/4GW Professional application with an old version of the debugger is to rename 4GWPRO.EXE to DOS4GW.EXE and make sure that it's either in the current directory or the first DOS4GW.EXE on the DOS PATH.

Tenberry will not provide technical support for this configuration; it's up to you to keep track of which DOS extender is which.

#### 8c. Meaning of "unexpected interrupt" message/error 2001.

In version 1.95 of DOS/4GW, we revised the "unexpected interrupt" message to make it easier to understand.

For example, the message:

```
Unexpected interrupt OE (code 0) at 168:10421034
```

is now printed:

```
error (2001): exception 0Eh (page fault) at 168:10421034
```

followed by a register dump, as before.

This message indicates that the processor detected some form of programming error and signaled an exception, which DOS/4GW trapped and reported. Exceptions which can be trapped include:

```
00h
       divide by zero
01h
       debug exception OR null pointer used
03h
       breakpoint
04h
       overflow
05h
       bounds
06h
       invalid opcode
07h
       device not available
08h
       double fault
09h
       overrun
       invalid TSS
0Ah
      segment not present
0Bh
      stack fault
0Ch
0Dh
      general protection fault
0Eh
       page fault
```

When you receive this message, this is the recommended course of action:

- 1. Record all of the information from the register dump.
- Determine the circumstances under which your program fails.
- Consult your debugger manual, or an Intel 386, 486 or Pentium Programmer's Reference Manual, to determine the circumstances under which the processor will generate the reported exception.
- Get the program to fail under your debugger, which should stop the program as soon as the exception occurs.
- Determine from the exception context why the processor generated an exception in this particular instance.

#### 8d. Meaning of "transfer stack overflow" message/error 2002.

In version 1.95 of DOS/4GW, we added more information to the "transfer stack overflow" message. The message (which is now followed by a register dump) is printed:

```
error (2002): transfer stack overflow
on interrupt <number> at <address>
```

This message means DOS/4GW detected an overflow on its interrupt handling stack. It usually indicates either a recursive fault, or a hardware interrupt handler that can't keep up with the rate at which interrupts are occurring. The best way to understand the problem is to use the VERBOSE option in DOS/4GW to dump the interrupt history on the transfer stack; see (8e) below.

#### 8e. Making the most of a DOS/4GW register dump.

If you can't understand your problem by running it under a debugger, the DOS/4GW register dump is your best debugging tool. To maximize the information available for postmortem debugging, set the environment variable DOS4G to VERBOSE, then reproduce the crash and record the output.

Here's a typical register dump with VERBOSE turned on, with annotations.

```
1 DOS/4GW error (2001): exception OEh (page fault)
                                       at 170:0042C1B2
2 TSF32: prev_tsf32 67D8
 SS 178 DS 178 ES 178 FS
EAX 1F000000 EBX 0 ECX 43201C EDX
ESI E EDI 0 EBP 431410 ESP
CS:IP 170:0042C1B2 ID 0E COD 0 FLG
                                              0 GS
                                              F.
                                         4313FC
                                         10246
4 CS= 170, USE32, page granular, limit FFFFFFF, base
                                                      0, acc CF9B
 SS= 178, USE32, page granular, limit FFFFFFFF, base DS= 178, USE32, page granular, limit FFFFFFFF, base
                                                       0, acc CF93
                                                      0, acc CF93
 ES= 178, USE32, page granular, limit FFFFFFF, base
                                                      0, acc CF93
                                                      15, acc 0
 FS=
      0, USE16, byte granular, limit 0, base
 GS=
      20, USE16, byte granular, limit
                                       FFFF, base
                                                    6AA0, acc 93
5 CRO: PG:1 ET:1 TS:0 EM:0 MP:0 PE:1 CR2: 1F000000 CR3: 9067
6 Crash address (unrelocated) = 1:000001B2
7 Opcode stream: 8A 18 31 D2 88 DA EB 0E 50 68 39 00 43 00 E8 1D
 Stack:
8 0178:004313FC 000E 0000 0000 0000 C2D5 0042 C057 0042 0170 0000 0000 0000
 0178:00431414 0450 0043 0452 0043 0000 0000 1430 0043 CBEF 0042 011C 0000
 0178:0043142C C568 0042 0000 0000 0000 0000 0000 F248 0042 F5F8 0042
 9 Last 4 ints: 21 @ 170:42CF48/21 @ 170:42CF48/21 @ 170:42CF48/E @ 170:42C1B2/
```

- 1. The error message includes a synopsis of the problem. In this case, the processor signaled a page fault exception while executing at address 170:0042C1B2.
- 2. The prev\_tsf32 field is not usually of interest.
- 3. These are the register values at the time of the exception. The interrupt number and error code (pushed on the stack by the processor for certain exceptions) are also printed.
- 4. The descriptors referenced by each segment register are described for your convenience. USE32 segments in general belong to your program; USE16 segments generally belong to the DOS extender. Here, CS points to your program's code segment, and SS, DS, and ES point to your data segment. FS is NULL and GS points to a DOS extender segment.
- 5. The control register information is not of any general interest, except on a page fault, when CR2 contains the address value that caused the fault. Since EAX in this case contains the same value, an attempt to dereference EAX could have caused this particular fault.
- 6. If the crash address (unrelocated) appears, it tells you where the crash occurred relative to your program's link map. You can therefore tell where a crash occurred even if you can't reproduce the crash in a debugger.
- 7. The opcode stream, if it appears, shows the next 16 bytes from the code segment at the point of the exception. If you disassemble these instructions, you can tell what instructions caused the crash, even without using a debugger. In this case, 8A 18 is the instruction mov bl, [eax].
- 8. 72 words from the top of the stack, at the point of the exception, may be listed next. You may be able to recognize function calls or data from your program on the stack.
- 9. The four interrupts least to most recently handled by DOS/4GW in protected mode are listed next. In this example, the last interrupt issued before the page fault occurred was an INT 21h (DOS call) at address 170:42CF48. Sometimes, this information provides helpful context.

Here's an abridged register dump from a stack overflow.

```
DOS/4GW error (2002): transfer stack overflow
                                 on interrupt 70h at 170:0042C002
 TSF32: prev_tsf32 48C8
                       170 ES
           C8 DS
                                     28 FS
                                                    0 GS
 EAX AAAAAAA EBX BBBBBBB ECX CCCCCCC EDX DDDDDDDD
 ESI 51515151 EDI D1D1D1D1 EBP B1B1B1B1 ESP
                                                 4884
1 CS:IP 170:0042C002 ID 70 COD
                                      0 FLG
                                                   2
2 Previous TSF:
 TSF32: prev_tsf32 498C
                       170 ES
                                     28 FS
                                                    0 GS
                                                                20
           C8 DS
 EAX AAAAAAA EBX BBBBBBB ECX CCCCCCC EDX DDDDDDDD
 ESI 51515151 EDI D1D1D1D1 EBP B1B1B1B1 ESP
                                                 4960
3 CS:IP 170:0042C002 ID 70 COD
                                      0 FLG
                                                   2
 Previous TSF:
 TSF32: prev_tsf32 67E4
          178 DS
                       170 ES
                                     28 FS
                                                    0 GS
                                                                20
 EAX AAAAAAA EBX BBBBBBB ECX CCCCCCC EDX DDDDDDDD
 ESI 51515151 EDI D1D1D1D1 EBP B1B1B1B1 ESP
                                               42FFE0
4 CS:IP 170:0042C039 ID 70 COD
                                      0 FLG
                                                 202
5 Opcode stream: CF 66 B8 62 25 66 8C CB 66 8E DB BA 00 CO 42 00
 Last 4 ints: 70 @ 170:42C002/70 @ 170:42C002/70 @ 170:42C002/70 @ 170:42C002/
```

1. We overflowed the transfer stack while trying to process an interrupt 70h at 170:0042C002.

- 2. The entire interrupt history from the transfer stack is printed next. The prev\_tsf32 numbers increase as we progress from most recent to least recent interrupt. All of these interrupts are still pending, which is why we ran out of stack space.
- 3. Before we overflowed the stack, we got the same interrupt at the same address. For a recursive interrupt situation, this is typical.
- 4. The oldest frame on the transfer stack shows the recursion was touched off at a slightly different address. Looking at this address may help you understand the recursion.
- 5. The opcode stream and last four interrupt information comes from the newest transfer stack frame, not the oldest.

### 14.9 Compatibility

#### 9a. Running DOS/4GW applications from inside Lotus 1-2-3.

In order to run DOS/4GW applications while "shelled out" from Lotus 1-2-3, you must use the PRIVATXM program included with your Open Watcom compiler. Otherwise, 1-2-3 will take all of the memory on your machine and prevent DOS/4GW from using it.

Before starting 1-2-3, you must set the DOS16M environment variable to limit Lotus' memory use (see your Open Watcom manual). After shelling out, you must run PRIVATXM, then clear the DOS16M environment variable before running your application.

#### 9b. EMM386.EXE provided with DOS 6.0.

We know of at least three serious bugs in the EMM386.EXE distributed with MS-DOS 6.0, one involving mis-counting the amount of available memory, one involving mapping too little of the High Memory Area (HMA) into its page tables, and one involving allocation of EMS memory. Version 1.95 of DOS/4GW contains workarounds for some of these problems.

If you are having problems with DOS/4GW and you are using an EMM386.EXE dated 3-10-93 at 6:00:00, or later, you may wish to try the following workarounds, in sequence, until the problem goes away.

- Configure EMM386 with both the NOEMS and NOVCPI options.
- Convert the DEVICEHIGH statements in your CONFIG.SYS to DEVICE statements, and remove the LH (Load High) commands from your AUTOEXEC.BAT.
- Run in a Windows DOS box.
- Replace EMM386 with another memory manager, such as QEMM-386, 386Max, or an older version of EMM386.
- Run with HIMEM.SYS alone.

You may also wish to contact Microsoft Corporation to inquire about the availability of a fix.

#### 9c. Spawning under OS/2 2.1.

We know of a bug in OS/2 2.1 that prevents one DOS/4GW application from spawning another over and over again. The actual number of repeated spawns that are possible under OS/2 varies from machine to machine, but is generally about 30.

This bug also affects programs running under other DOS extenders, and we have not yet found a workaround, other than linking your two programs together as a single program.

#### 9d. "DPMI host error: cannot lock stack".

This error message almost always indicates insufficient memory, rather than a real incompatibility. If you see it under an OS/2 DOS box, you probably need to edit your DOS Session settings and make DPMI\_MEMORY\_LIMIT larger.

#### 9e. Bug in Novell TCPIP driver.

Some versions of a program from Novell called TCPIP.EXE, a real-mode program, will cause the high words of EAX and EDX to be altered during a hardware interrupt. This bug breaks protected-mode software (and other real-mode software that uses the 80386 registers). Novell has released a newer version of TCPIP that fixes the problem; contact Novell to obtain the fix.

#### 9f. Bugs in Windows NT.

The initial release of Windows NT includes a DPMI host, DOSX.EXE, with several serious bugs, some of which apparently cannot be worked around. We cannot warranty operation of DOS/4GW under Windows NT at this time, but we are continuing to exercise our best efforts to work around these problems.

You may wish to contact Microsoft Corporation to inquire about the availability of a new version of DOSX.EXE.

# Windows 3.x Programming Guide

# 15 Creating 16-bit Windows 3.x Applications

This chapter describes how to compile and link 16-bit Windows 3.x applications simply and quickly. In this chapter, we look at applications written to exploit the Windows 3.x Application Programming Interface (API).

We will illustrate the steps to creating 16-bit Windows 3.x applications by taking a small sample application and showing you how to compile, link, run and debug it.

Note - It is supposed you are working on the host with Windows 3.x installed. If you are on the host with any other operating system you should setup INCLUDE environment variable correctly to compile for 16-bit Windows 3.x target.

```
You can do that by command (DOS, OS/2, NT)
set INCLUDE=%WATCOM%\h;%WATCOM%\h\win
or by command (LINUX)
export INCLUDE=$WATCOM/h:$WATCOM/h/win
```

### 15.1 The Sample GUI Application

To demonstrate the creation of 16-bit Windows 3.x applications, we introduce a simple sample program. The following example is the "hello" program adapted for Windows.

```
#include <windows.h>
int PASCAL WinMain ( HANDLE hInstance, HANDLE hPrevInst,
                    LPSTR lpCmdLine, int nCmdShow )
   MessageBox ( NULL, "Hello world",
                "Open Watcom C/C++ for Windows",
                MB_OK | MB_TASKMODAL );
    return(0);
}
```

The goal of this program is to display the message "Hello world" on the screen. The MessageBox Windows API function is used to accomplish this task. We will take you through the steps necessary to produce this result.

### 15.2 Building and Running the GUI Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl -l=windows -bt=windows hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl -l=windows -bt=windows hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc hello.c -bt=windows
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 37
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 16-bit executable
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries).

The resultant 16-bit Windows 3.x application HELLO. EXE can now be run under Windows 3.x.

### 15.3 Debugging the GUI Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the *WCL* command, this is fairly straightforward. *WCL* recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl -l=windows -bt=windows -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl -l=windows -bt=windows -d2 hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc hello.c -bt=windows -d2
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 58
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 16-bit executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, select the Open Watcom Debugger icon. It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.

## 16 Porting Non-GUI Applications to 16-bit Windows 3.x

Generally, an application that is to run in a windowed environment must be written in such a way as to exploit the Windows Application Programming Interface (API). To take an existing character-based (i.e., non-graphical) application that ran under a system such as DOS and adapt it to run under Windows can require some considerable effort. There is a steep learning curve associated with the API function libraries.

This chapter describes how to create a Windows application quickly and simply from an application that does not use the Windows API. The application will make use of Open Watcom's default windowing support.

Suppose you have a set of C/C++ applications that previously ran under a system like DOS and you now wish to run them under Windows 3.x. To achieve this, you can simply recompile your application with the appropriate options and link with the appropriate libraries. We provide a default windowing system that turns your character-mode application into a simple Windows 3.x Graphical User Interface (GUI) application.

Normally, a Windows 3.x GUI application makes use of user-interface tools such as menus, icons, scroll bars, etc. However, an application that was not designed as a windowed application (such as a DOS application) can run as a GUI application. This is achieved by our default windowing system. The following sections describe the default windowing system.

### 16.1 Console Device in a Windowed Environment

In a C/C++ application that runs under DOS, stdin (C++cin) and stdout (C++cout) are connected to the standard input and standard output devices respectively. It is not a recommended practice to read directly from the standard input device or write to the standard output device when running in a windowed environment. For this reason, a default windowing environment is created for C/C++ applications that read from stdin(C++cin) or write to stdout(C++cout). When your application is started, a window is created in which output to stdout (C++cout) is displayed and input from stdin (C++cin) is requested.

In addition to the standard I/O device, it is also possible to perform I/O to the console by explicitly opening a file whose name is "CON". When this occurs, another window is created and displayed. This window is different from the one created for standard input and standard output. In fact, every time you open the console device a different window is created. This provides a simple multi-windowing system for multiple streams of data to and from the console device.

### 16.2 The Sample Non-GUI Application

To demonstrate the creation of 16-bit Windows 3.x applications, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
{
    printf( "Hello world\n" );
}
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
{
    cout << "Hello world" << endl;
}</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

### 16.3 Building and Running the Non-GUI Application

Very little effort is required to port an existing C/C++ application to Windows 3.x.

You must compile and link the file hello.c specifying the "bw" option.

```
C>wcl -l=windows -bw -bt=windows hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl -l=windows -bw -bt=windows hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
       wcc hello.c -bw -bt=windows
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 155, 0 warnings, 0 errors
Code size: 17
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 16-bit executable
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries).

The resultant 16-bit Windows 3.x application HELLO. EXE can now be run under Windows 3.x as a Windows GUI application.

### 16.4 Debugging the Non-GUI Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL command, this is fairly straightforward. WCL recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl -l=windows -bw -bt=windows -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl -l=windows -bw -bt=windows -d2 hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc hello.c -bw -bt=windows -d2
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 155, 0 warnings, 0 errors
Code size: 23
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 16-bit executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, select the Open Watcom Debugger icon. It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.

### 16.5 Default Windowing Library Functions

A few library functions have been written to enable some simple customization of the default windowing system's behaviour. The following functions are supplied:

#### \_dwDeleteOnClose

```
int _dwDeleteOnClose( int handle );
```

This function tells the console window that it should close itself when the file is closed. You must pass to it the handle associated with the opened console.

#### \_dwSetAboutDlg

```
int _dwSetAboutDlg( const char *title, const char *text );
```

This function sets the about dialog box of the default windowing system. The "title" points to the string that will replace the current title. If title is NULL then the title will not be replaced. The "text" points to a string which will be placed in the about box. To get multiple lines, embed a new line after each logical line in the string. If "text" is NULL, then the current text in the about box will not be replaced.

#### \_dwSetAppTitle

```
int _dwSetAppTitle( const char *title );
```

This function sets the main window's title.

#### \_dwSetConTitle

```
int _dwSetConTitle( int handle, const char *title );
```

This function sets the console window's title which corresponds to the handle passed to it.

#### \_dwShutDown

```
int _dwShutDown( void );
```

This function shuts down the default windowing I/O system. The application will continue to execute but no windows will be available for output.

#### dwYield

```
int _dwYield( void );
```

This function yields control back to the operating system, thereby giving other processes a chance to run.

These functions are described more fully in the WATCOM C Library Reference.

# 17 Creating 32-bit Windows 3.x Applications

This chapter describes how to compile and link 32-bit Windows 3.x applications simply and quickly. In this chapter, we look at applications written to exploit the Windows 3.x Application Programming Interface (API).

We will illustrate the steps to creating 32-bit Windows 3.x applications by taking a small sample application and showing you how to compile, link, run and debug it.

Note - It is supposed you are working on the host with Windows 3.x installed. If you are on the host with any other operating system you should setup INCLUDE environment variable correctly to compile for 32-bit Windows 3.x target.

```
You can do that by command (DOS, OS/2, NT)
set INCLUDE=%WATCOM%\h;%WATCOM%\h\win
or by command (LINUX)
export INCLUDE=$WATCOM/h:$WATCOM/h/win
```

### 17.1 The Sample GUI Application

To demonstrate the creation of 32-bit Windows 3.x applications, we introduce a simple sample program. The following example is the "hello" program adapted for Windows.

```
#include <windows.h>
int PASCAL WinMain ( HANDLE hInstance, HANDLE hPrevInst,
                    LPSTR lpCmdLine, int nCmdShow )
   MessageBox ( NULL, "Hello world",
                "Open Watcom C/C++ for Windows",
                MB_OK | MB_TASKMODAL );
    return(0);
}
```

The goal of this program is to display the message "Hello world" on the screen. The MessageBox Windows API function is used to accomplish this task. We will take you through the steps necessary to produce this result.

### 17.2 Building and Running the GUI Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl386 -l=win386 -bt=windows hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=win386 -bt=windows hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bt=windows
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 41
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 32-bit executable
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.rex (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). The ".rex" file must now be combined with Open Watcom's 32-bit Windows supervisor WIN386.EXT using the Open Watcom Bind utility. WBIND.EXE combines your 32-bit application code and data (".rex" file) with the 32-bit Windows supervisor. The process involves the following steps:

- 1. WBIND copies WIN386.EXT into the current directory.
- 2. WBIND. EXE optionally runs the resource compiler on the 32-bit Windows supervisor so that the 32-bit executable can have access to the applications resources.
- 3. WBIND.EXE concatenates WIN386.EXT and the ".rex" file, and creates a ".exe" file with the same name as the ".rex" file.

The following describes the syntax of the WBIND command.

```
WBIND file_spec [-d] [-n] [-q] [-s supervisor] [-R rc_options]
```

The square brackets [ ] denote items which are optional.

**WBIND** is the name of the Open Watcom Bind utility.

file\_spec is the name of the 32-bit Windows EXE to bind.

-d requests that a 32-bit DLL be built.

indicates that the resource compiler is NOT to be invoked. -n

requests that WBIND run in quiet mode (no informational messages are -q

displayed).

-s supervisor specifies the path and name of the Windows supervisor to be bound with the

> application. If not specified, a search of the paths listed in the PATH environment variable is performed. If this search is not successful and the

WATCOM environment variable is defined, the %WATCOM%\BINW directory is

searched.

-R rc\_options all options after -R are passed to the resource compiler.

To bind our example program, the following command may be issued:

```
C>wbind hello -n
```

If the "s" option is specified, it must identify the location of the WIN386.EXT file or the W386DLL.EXT file (if you are building a DLL).

#### Example:

```
C>wbind hello -n -s c:\watcom\binw\win386.ext
```

If the "s" option is not specified, then the WATCOM environment variable must be defined or the "BINW" directory must be listed in your **PATH** environment variable.

#### Example:

```
C>set watcom=c:\watcom
C>path c:\watcom\binw;c:\dos;c:\windows
```

The resultant 32-bit Windows 3.x application HELLO. EXE can now be run under Windows 3.x.

### 17.3 Debugging the GUI Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL386 command, this is fairly straightforward. WCL386 recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl386 -l=win386 -bt=windows -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=win386 -bt=windows -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bt=windows -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 66
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 32-bit executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL386 will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

Once again, the ".rex" file must be combined with Open Watcom's 32-bit Windows supervisor WIN386.EXT using the Open Watcom Bind utility. This step is described in the previous section.

To request the Open Watcom Debugger to assist in debugging the application, select the Open Watcom Debugger icon. It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled Open Watcom Debugger User's Guide.

## 18 Porting Non-GUI Applications to 32-bit Windows 3.x

Generally, an application that is to run in a windowed environment must be written in such a way as to exploit the Windows Application Programming Interface (API). To take an existing character-based (i.e., non-graphical) application that ran under a system such as DOS and adapt it to run under Windows can require some considerable effort. There is a steep learning curve associated with the API function libraries.

This chapter describes how to create a Windows application quickly and simply from an application that does not use the Windows API. The application will make use of Open Watcom's default windowing support.

Suppose you have a set of C/C++ applications that previously ran under a system like DOS and you now wish to run them under Windows 3.x. To achieve this, you can simply recompile your application with the appropriate options and link with the appropriate libraries. We provide a default windowing system that turns your character-mode application into a simple Windows 3.x Graphical User Interface (GUI) application.

Normally, a Windows 3.x GUI application makes use of user-interface tools such as menus, icons, scroll bars, etc. However, an application that was not designed as a windowed application (such as a DOS application) can run as a GUI application. This is achieved by our default windowing system. The following sections describe the default windowing system.

## 18.1 Console Device in a Windowed Environment

In a C/C++ application that runs under DOS, stdin (C++cin) and stdout (C++cout) are connected to the standard input and standard output devices respectively. It is not a recommended practice to read directly from the standard input device or write to the standard output device when running in a windowed environment. For this reason, a default windowing environment is created for C/C++ applications that read from stdin(C++cin) or write to stdout(C++cout). When your application is started, a window is created in which output to stdout (C++cout) is displayed and input from stdin (C++cin) is requested.

In addition to the standard I/O device, it is also possible to perform I/O to the console by explicitly opening a file whose name is "CON". When this occurs, another window is created and displayed. This window is different from the one created for standard input and standard output. In fact, every time you open the console device a different window is created. This provides a simple multi-windowing system for multiple streams of data to and from the console device.

## 18.2 The Sample Non-GUI Application

To demonstrate the creation of 32-bit Windows 3.x applications, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
{
    printf( "Hello world\n" );
}
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
{
    cout << "Hello world" << endl;
}</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

## 18.3 Building and Running the Non-GUI Application

Very little effort is required to port an existing C/C++ application to Windows 3.x.

You must compile and link the file hello.c specifying the "bw" option.

```
C>wcl386 -l=win386 -bw -bt=windows hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=win386 -bw -bt=windows hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
       wcc386 hello.c -bw -bt=windows
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 24
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 32-bit executable
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.rex (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). The ".rex" file must now be combined with Open Watcom's 32-bit Windows supervisor WIN386.EXT using the Open Watcom Bind utility. WBIND.EXE combines your 32-bit application code and data (".rex" file) with the 32-bit Windows supervisor. The process involves the following steps:

- 1. WBIND copies WIN386.EXT into the current directory.
- 2. WBIND. EXE optionally runs the resource compiler on the 32-bit Windows supervisor so that the 32-bit executable can have access to the applications resources.
- 3. WBIND.EXE concatenates WIN386.EXT and the ".rex" file, and creates a ".exe" file with the same name as the ".rex" file.

The following describes the syntax of the WBIND command.

#### WBIND file\_spec [-d] [-n] [-q] [-s supervisor] [-R rc\_options]

The square brackets [] denote items which are optional.

**WBIND** is the name of the Open Watcom Bind utility.

*file\_spec* is the name of the 32-bit Windows EXE to bind.

*-d* requests that a 32-bit DLL be built.

-n indicates that the resource compiler is NOT to be invoked.

-q requests that WBIND run in quiet mode (no informational messages are

displayed).

-s supervisor specifies the path and name of the Windows supervisor to be bound with the

application. If not specified, a search of the paths listed in the **PATH** environment variable is performed. If this search is not successful and the **WATCOM** environment variable is defined, the <code>%WATCOM%\BINW</code> directory is

searched.

-R rc\_options all options after -R are passed to the resource compiler.

To bind our example program, the following command may be issued:

C>wbind hello -n

If the "s" option is specified, it must identify the location of the WIN386.EXT file or the W386DLL.EXT file (if you are building a DLL).

#### Example:

```
C>wbind hello -n -s c:\watcom\binw\win386.ext
```

If the "s" option is not specified, then the **WATCOM** environment variable must be defined or the "BINW" directory must be listed in your **PATH** environment variable.

#### Example:

```
C>set watcom=c:\watcom
   or
C>path c:\watcom\binw;c:\dos;c:\windows
```

The resultant 32-bit Windows 3.x application HELLO.EXE can now be run under Windows 3.x as a Windows GUI application.

## 18.4 Debugging the Non-GUI Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the *WCL386* command, this is fairly straightforward. *WCL386* recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl386 -l=win386 -bw -bt=windows -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=win386 -bw -bt=windows -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bw -bt=windows -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 45
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows 32-bit executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. *WCL386* will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

Once again, the ".rex" file must be combined with Open Watcom's 32-bit Windows supervisor WIN386.EXT using the Open Watcom Bind utility. This step is described in the previous section.

To request the Open Watcom Debugger to assist in debugging the application, select the Open Watcom Debugger icon. It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled Open Watcom Debugger User's Guide.

## 18.5 Default Windowing Library Functions

A few library functions have been written to enable some simple customization of the default windowing system's behaviour. The following functions are supplied:

#### \_dwDeleteOnClose

```
int _dwDeleteOnClose( int handle );
```

This function tells the console window that it should close itself when the file is closed. You must pass to it the handle associated with the opened console.

#### \_dwSetAboutDlg

```
int _dwSetAboutDlg( const char *title, const char *text );
```

This function sets the about dialog box of the default windowing system. The "title" points to the string that will replace the current title. If title is NULL then the title will not be replaced. The "text" points to a string which will be placed in the about box. To get multiple lines, embed a new line after each logical line in the string. If "text" is NULL, then the current text in the about box will not be replaced.

#### \_dwSetAppTitle

```
int _dwSetAppTitle( const char *title );
```

This function sets the main window's title.

#### \_dwSetConTitle

```
int _dwSetConTitle( int handle, const char *title );
```

This function sets the console window's title which corresponds to the handle passed to it.

#### dwShutDown

```
int _dwShutDown( void );
```

This function shuts down the default windowing I/O system. The application will continue to execute but no windows will be available for output.

## Windows 3.x Programming Guide

```
_dwYield
```

```
int _dwYield( void );
```

This function yields control back to the operating system, thereby giving other processes a chance to run.

These functions are described more fully in the WATCOM C Library Reference.

# 19 The Open Watcom 32-bit Windows 3.x Extender

Open Watcom C/C++ contains the necessary tools and libraries to create 32-bit applications for Windows 3.x. Using Open Watcom C/C++ gives the programmer the benefits of a 32-bit flat memory model and access to the full Windows API (along with the usual C/C++ library functions).

The general model of the environment is as follows: The 32-bit flat memory model program is linked against a special 32-bit Windows library. This library contains the necessary information to invoke special 16-bit functions, which lie in the supervisor (WIN386.EXT). The 32-bit program is then bound (using WBIND.EXE) with the supervisor to create a Windows executable. At the same time as the 32-bit program is being bound, the resource compiler is run on the supervisor, and all the resources for the application are placed there. When the application is started, the supervisor obtains the 32-bit memory, relocates the 32-bit application into the memory, and invokes the 32-bit application.

All Windows functions are invoked from the supervisor, and all callback routines lie within the supervisor. The local heap resides within the supervisor as well.

If you are starting from a 16-bit Windows application, most of the code will not change when you port it to the 32-bit Windows environment. However, because of the nature of the Windows API and its implicit dependencies on a 16-bit environment, some source changes are necessary. These source changes are minimal, and are backwards compatible with the 16-bit environment.

## 19.1 Pointers

Throughout this document, there will be references to both *near* and *far*, and *16-bit* and *32-bit* pointers. Since this can rapidly become confusing, some initial explanations will be given here.

A *far pointer* is a pointer that is composed of both a selector and an offset. A selector determines a specific region of memory, and the offset is relative to the start of this region. A *near pointer* is a pointer that has an offset only, the selector is automatically assumed by the CPU.

The problem with far pointers is the selector overhead. Using a far pointer is much more expensive than using a near pointer. This is the advantage of the 32-bit flat memory model - all pointers within the program are near, and yet you can address up to 4 gigabytes of memory.

A *16-bit near pointer* occupies 2 bytes of memory (i.e., the offset is 16 bits long). This pointer can reference up to 64K of data.

A *16-bit far pointer* occupies 4 bytes of memory. There is a 16-bit selector and a 16-bit offset. This pointer can reference up to 64K of data.

A *32-bit near pointer* occupies 4 bytes of memory (i.e., the offset is 32 bits long). This pointer can reference up to 4 gigabytes of data.

A *32-bit far pointer* occupies 6 bytes of memory. There is a 16-bit selector and a 32-bit offset. This pointer can reference up to 4 gigabytes of data.

Windows, in general, uses 16-bit far pointers to pass information around. These 16-bit far pointers can also be used by a 32-bit Windows application. Using a special macro, MK\_FP32, the offset of the 16-bit far pointer is extended from 16 bits to 32 bits, and the pointer becomes a 32-bit far pointer. The 32-bit far pointer is then used by the application to access the data (note that offsets still must be less than 64K, since the selector is still for a 64K data area).

## 19.2 Implementation Overview

This section provides an overview of the issues that require consideration when creating a 32-bit Windows application for a 16-bit Windows environment.

First, all modules have to be recompiled for the 32-bit flat memory model with a compiler capable of generating 32-bit instructions. Many Windows API functions take *int* as a parameter. This *int* is from the 16-bit world, and is 2 bytes long. In the 32-bit world, this *int* becomes 4 bytes long. Since Windows is only expecting two bytes of data, all occurrences of int have to be changed to short in WINDOWS.H.

Pointers to data passed to Windows are all far pointers. We will be passing pointers to data in our 32-bit flat address space, and these pointers are near pointers. By simply getting rid of all *far* keywords in WINDOWS.H, all pointers will now be passed as 32-bit near pointers. As well, notice that these 32-bit near pointers are the same size as as their 16-bit far pointer counterparts (4 bytes). This is good, since all data structures containing pointers will remain the same size.

Windows cannot be called from 32-bit code on a 32-bit stack. This means that in order to call the API functions, it is necessary to write a set of cover functions that will accept the parameters, switch into a 16-bit environment, and then call Windows. There is another issue, though. Windows only understands 16-bit pointers, so before calling Windows, all pointers being passed to Windows must be converted to 16-bit far pointers.

It turns out that Windows can also call back to your application. Windows can only call 16-bit code, though, so there is a need for a bridge from the 16-bit side to the 32-bit side. It is necessary to allocate 16-bit call back routines that can be passed to Windows. These call back routines will then switch into the 32-bit environment and call whatever 32-bit function is required. The 32-bit call back has to be declared as a far function, since it is necessary to issue a far call to enter it from the 16-bit side. If it is a far function, then the compiler will generate the appropriate code for it to return from the far call.

Once Windows calls you back, it can hand you 16-bit far pointers in a long (4 byte) parameter. This pointer can only be used in the 32-bit environment if it is a 32-bit far pointer, not a 16-bit far pointer. The conversion is simple: the 16-bit offset is extended to a 32-bit offset (the high word is zeroed out). Any far pointer that Windows hands to you must be converted in this way.

Sometimes, a Windows application wants to call a procedure in a DLL. The procedure address is a 16-bit far pointer. It is not possible to issue an indirect call to this address from the 32-bit environment, so some sort of interface is needed. This interface would switch into the 16-bit environment, and then call the 16-bit

These issues, along with other minor items, are handled by Open Watcom C/C++, and are discussed in more technical detail in later sections.

## 19.3 System Structure



Figure 5. WIN386 Structure



Figure 6. 32-bit Application Structure

## 19.4 System Overview

- WIN386.EXT is the key component of a 32-bit Windows application. It is a 16-bit Windows application which contains:
  - All application resources.
  - A 16-bit local heap.
  - A 16-bit stack.
- W386DLL.EXT is similar to WIN386.EXT, only it provides a DLL interface.

WIN386.EXT is bound to your 32-bit application to create a 32-bit application that will run under Windows 3.x. WIN386.EXT provides the following functionality:

- supervisor to bring the 32-bit application into memory and start it running.
- "glue" functions to connect to Windows for both API and DOS functionality. This interface is designed to transparently set up the calling functions' pointers and parameters to their 16-bit counterparts.
- "glue-back" functions to allow Windows to call back 32-bit routines.
- special code to allow debugging of 32-bit applications.
- WINDOWS . H has been specially modified for use in the 32-bit Windows environment. As well, it contains all special definitions for 32-bit applications.
- WIN386. LIB contains all the necessary library functions to connect to the 32-bit supervisor WIN386.EXT. All Windows API calls and Open Watcom C/C++ library DOS calls are found here.
- The standard C/C++ library functions, specially modified to run in the 32-bit environment, are located in the \WATCOM\LIB386\WIN directory.
- WBIND. EXE merges your 32-bit executable and the appropriate Supervisor into a single executable.

## 19.5 Steps to Obtaining a 32-bit Application

The following is an overview of the procedure for creating a 32-bit Windows Application:

- If you are starting with a 16-bit Windows application, you must adapt your source code to the 32-bit environment.
- You must compile the application using a 32-bit compiler.
- You must link the application with the 32-bit libraries.
- You must bind the 32-bit application with the 32-bit supervisor.
- You can then run and/or debug the application.

# **20** Windows 3.x 32-bit Programming Overview

This chapter includes the following topics:

- WINDOWS.H
- Environment Notes
- Floating-point Emulation
- Multiple Instances
- Pointer Handling
- When To Convert Incoming Pointers
- When To Convert Outgoing Pointers
- SendMessage and SendDlgItemMessage
- GlobalAlloc and LocalAlloc
- Callback Function Pointers
- Window Sub-classing
- Calling 16-bit DLLs
- Making DLL Calls Transparent
- Far Pointer Manipulation
- \_16 Functions

## 20.1 WINDOWS.H

When developing programs, make sure WINDOWS. H is included as the first include file in all source files. This header file contains only the following lines:

```
#ifdef _WINDOWS_16_
#include <win16.h>
#else
#include <_win386.h>
#endif
```

The file WIN16.H is the regular 16-bit Windows header file, and is only conditionally included for 16-bit Windows applications. The file \_WIN386.H contains all the prototypes and macros for the 32-bit environment, as well as including and modifying WIN16.H. These modifications are changing int to

short, and changing the *far* keyword to nothing. These changes (that ONLY apply to things defined in WIN16.H) cause all integers to be 16-bit integers, and all LP... pointer types to be near pointers.

Other include files for Windows must be specifically requested by defining macros before including WINDOWS.H. This is required so that the same changes made to the primary Windows header file will apply to routines declared in the other header files.

Macro name	File included
#define INCLUDE_COMMDLG_H	COMMDLG.H
#define INCLUDE_CUSTCNTL_H	CUSTCNTL.H
#define INCLUDE_DDE_H	DDE.H
#define INCLUDE_DDEML_H	DDEML.H
#define INCLUDE_DRIVINIT_H	DRIVINIT.H
#define INCLUDE_LZEXPAND_H	LZEXPAND.H
#define INCLUDE_MMSYSTEM_H	MMSYSTEM.H
#define INCLUDE_OLE_H	OLE.H
#define INCLUDE_PENWIN_H	PENWIN.H
#define INCLUDE_PENWOEM_H	PENWOEM.H
#define INCLUDE_PRINT_H	PRINT.H
#define INCLUDE_SHELLAPI_H	SHELLAPI.H
#define INCLUDE_STRESS_H	STRESS.H
#define INCLUDE_TOOLHELP_H	TOOLHELP.H
#define INCLUDE_VER_H	VER.H

## 20.2 Environment Notes

- The Windows functions *Catch* and *Throw* save only the 16-bit state. Instead of these functions, use the *setjmp* and *longjmp* functions.
- The 32-bit Windows Supervisor uses the first 256 bytes of the 32-bit application's stack to save state information. If this is corrupted, your application will abnormally terminate.
- The 32-bit Windows Supervisor provides resources for up to 512 callback routines. Note that this restriction is only on the maximum number of active callbacks.

## 20.3 Floating-point Emulation

The file WEMU387.386 is included to support floating-point emulation for 32-bit applications running under Windows. This file is installed in the [386Enh] section of your SYSTEM.INI file. By using the floating-point emulator, your application can be compiled with the "fpi87" option to use inline floating-point instructions, and it will run on a machine without a numeric coprocessor.

Only one of WEMU387.386 and WDEBUG.386 may be installed in your [386Enh] section. WEMU387.386 may be distributed with your application.

## 20.4 Multiple Instances

Since the 32-bit application resides in a flat memory space, it is NOT possible to share code with other instances. This means that you must register new window classes with callbacks into the new instance's code space. A simple way of accomplishing this is as follows:

```
int PASCAL WinMain ( HANDLE hInstance,
                    HANDLE hPrevInstance;
                    LPSTR lpCmdLine,
                    int nCmdShow );
{
    WNDCLASS wc;
    HWND
            hWnd
              class[32];
    char
    wc.style = NULL;
    wc.lpfnWndProc = (LPVOID) MainWndProc;
    wc.cbClsExtra = 0;
    wc.cbWndExtra = 0;
    wc.hInstance = hInstance;
    wc.hIcon = LoadIcon( NULL, IDI_APPLICATION );
    wc.hCursor = LoadCursor( NULL, IDC_ARROW );
    wc.hbrBackground = GetStockObject( WHITE_BRUSH );
    wc.lpszMenuName = "Menu";
    sprintf( class, "Class%d", hInstance );
    wc.lpszClassName = class;
    RegisterClass( &wc );
    hWnd = CreateWindow(
        class,
        "Application",
        WS_OVERLAPPEDWINDOW,
        CW_USEDEFAULT,
        CW_USEDEFAULT,
        CW_USEDEFAULT,
        CW_USEDEFAULT,
        NULL,
        NULL,
        hInstance,
        NULT.
    );
```

The variable *class* contains a unique name based on the instance of the application.

## 20.5 Pointer Handling

Windows 3.x is a 16-bit operating system. Function pointers that Windows deals with are 16-bit far pointers, and any data you communicate to Windows with are 16-bit far pointers. 16-bit far pointers occupy 4 bytes of data, and are capable of addressing up to 64K. For data objects larger than 64K, huge pointers are used (a sequence of far pointers that map out consecutive 64K segments for the data object). 16-bit far pointers are expensive to use due to the overhead of selector loads (each time you use the pointer, a segment register must have a value put in it). 16-bit huge pointers are even more expensive: not only is there the overhead of selector loads, but a run-time call is necessary to perform any pointer arithmetic.

In a 32-bit flat memory model, such as that of the Open Watcom C/C++ for Windows environment, all pointers are 32-bit near pointers (occupying 4 bytes of data as well). However, these pointers may access objects of up to 4 gigabytes in size, and there is no selector load overhead.

All Windows defined pointer types (e.g., LPSTR) are by default near pointers, not far pointers. To obtain a far pointer, the far keyword must be explicitly coded, i.e., char far \*foo, rather than LPSTR foo. A 32-bit near pointer is the same size as a 16-bit far pointer, so that all Windows pointers are the same size in the 32-bit flat memory model as they are in the original 16-bit segmented model.

For a 32-bit environment to communicate with Windows 3.x, there are some considerations. All pointers sent to Windows must be converted from 32-bit near pointers to 16-bit far pointers. These conversions are handled by the Supervisor.

It is important to remember that all API functions which accept pointers (with the exception of functions that accept function pointers) accept 32-bit near pointers in this 32-bit model. If you attempt to pass a 32-bit far pointer, the conversion will not take place correctly.

16-bit far pointers to data may be passed into the API functions, and the Supervisor will not do any conversion.

Incoming pointers must be converted from 16-bit far pointers to 32-bit far pointers. This conversion is a trivial one: the offset portion of the 16-bit far pointer is extended to 32-bits. Pointers from Windows are by their nature far (that is, the data is pointed to by its own selector), and must be used as far in the 32-bit environment. Of course, conversions are only required if you actually need to reference the pointer.

Function pointers (i.e., pointers to callback routines) used by Windows are not converted from 32-bit to 16-bit. Rather, a 16-bit thunking layer that transfers control from the 16-bit environment to the 32-bit environment must be used. This thunking layer is provided by the Supervisor.

## 20.5.1 When To Convert Incoming Pointers

Whenever you wish to use a pointer passed to you by Windows, you must convert it to a 32-bit far pointer. If you are passed a 16-bit far pointer, the macro  $MK\_FP32$  can be used to convert it to a 32-bit far pointer. If you are passed a 16-bit near pointer (e.g., from LocalLock), then the macro  $MK\_LOCAL32$  can be used to convert it to a 32-bit far pointer.

Some places where pointer conversion may be required are:

- LocalLock
- GlobalLock
- the lParam in a window callback routine (if it is a pointer)

## 20.5.2 When To Convert Outgoing Pointers

Typically, there is no need to do any kind of conversions on your pointers when passing them to Windows. The Supervisor handles all 32-bit to 16-bit translations for you, in the case of the regular Windows API functions. However, if you are passing a 32-bit pointer to some other 16-bit application in the Windows environment, then pointer conversions must by done. There are two types of "outgoing" pointers: data pointers and function pointers.

Function pointers (to callback routines) must have a thunking layer provided, using the *GetProc16* function (this is explained in detail in a later section).

Data pointers can be translated from 32-bit to 16-bit using the AllocAlias16 and AllocHugeAlias16 functions. These functions create 16-bit far pointers that have the same linear address as the 32-bit near pointer that was converted.

It is important to remember that when passing a pointer to a data structure in this fashion, any pointers in the data structure must also be converted.

The Supervisor will convert any pointers that it knows about; but there are some complications created by the fact that Windows allows you to pass pointers in functions that are prototyped to take a long integer.

The Windows API functions SendMessage and SendDlgItemMessage rely on other fields determining the nature of the long data item that they accept; this is discussed in detail in the next section.

#### 20.5.2.1 SendMessage and SendDigitemMessage

SendMessage and SendDlgItemMessage have special cover functions that determine when the long integer is really a pointer and needs to be converted. These cover functions are used automatically, unless the macro NOCOVERSENDS is defined before including WINDOWS. Has in the following example.

```
#define NOCOVERSENDS
#include <windows.h>
```

SendMessage and SendDlgItemMessage will do pointer conversions automatically using AllocAlias16 and FreeAlias16 (unless NOCOVERSENDS is defined) for the following message types:

- combo boxes (CB\_ messages)
- edit controls (EM\_ messages)
- list boxes (LB\_ messages)
- certain windows messages (WM\_ messages);

The messages that are intercepted by the cover functions for **SendMessage** and **SendDlgItemMessage** are:

CB_ADDSTRING CB_FINDSTRINGEXACT CB_SELECTSTRING	CB_DIR CB_GETLBTEXT	CB_FINDSTRING CB_INSERTSTRING
EM_GETLINE EM_SETRECT	EM_GETRECT EM_SETRECTNP	EM_REPLACESEL EM_SETTABSTOPS
LB_ADDSTRING LB_FINDSTRINGEXACT LB_GETTEXT LB_SETTABSTOPS	LB_DIR LB_GETITEMRECT LB_INSERTSTRING	LB_FINDSTRING LB_GETSELITEMS LB_SELECTSTRING
WM_MDICREATE	WM_NCCALCSIZE	

Note that for SendMessage and SendDlgItemMessage, some of the messages may NOT require pointer conversion:

- CB\_ADDSTRING, CB\_FINDSTRING, CB\_FINDSTRINGEXACT, CB\_INSERTSTRING will not need a conversion if the combo box was created as owner-draw style without CBS\_HASSTRINGS style.
- LB\_ADDSTRING, LB\_FINDSTRING, LB\_FINDSTRINGEXACT, LB\_INSERTSTRING will not need a conversion if the list box was created as owner-draw style without LBS\_HASSTRINGS style.

The macro *NOCOVERSENDS* should be defined in modules where messages like these are being sent. With these messages, the lParam data item does not contain a pointer, and the automatic pointer conversion would be incorrect. By doing

```
#define NOCOVERSENDS
#include "windows.h"
```

modules that send messages like the above will not have the pointer conversion performed.

#### 20.5.3 GlobalAlloc and LocalAlloc

The functions *GlobalAlloc* and *LocalAlloc* are the typical way of allocating memory in the 16-bit Windows environment. In the 32-bit environment, there is no need to use these functions. The only time *GlobalAlloc* is needed is when allocating shared memory, i.e., *GMEM\_DDESHARE*.

The C runtime functions *malloc* and *free* manipulate your 32-bit near heap for you. By using these functions to allocate memory, you may create data objects as large as the enhanced mode Windows memory manager will permit.

#### 20.5.4 Callback Function Pointers

To access a callback function, an instance of it must be created using *MakeProcInstance*. This creates a "thunk" (a special piece of code) that automatically puts the application's data segment into the AX register, and then calls the specified callback function.

In Windows 3.x, it is not possible to do a *MakeProcInstance* directly on a 32-bit callback routine, since Windows 3.x does not understand 32-bit applications. Therefore, it is necessary to use a 16-bit callback routine that passes control to the 32-bit callback routine. This 16-bit callback routine is automatically created by the Supervisor when using any of the standard Windows API functions that accept a callback routine.

The 16-bit callback routine for a 32-bit application is a special layer that transfers the parameters from a 16-bit stack to the 32-bit stack, and then passes control to 32-bit code. These 16-bit callback routines are found in the Supervisor. The function *GetProc16* provides pointers to these 16-bit callback routines.

However, it is not often necessary to use the *GetProc16* function to obtain a 16-bit/32-bit callback interface function.

In the general case, one would have to write code as follows:

```
#define NOAUTOPROCS
#include <windows.h>
CALLBACKPTR
                pCb;
FARPROC
                fpProc;
pCb = GetProc16( A_Function, GETPROC_callbacktype );
fpProc = MakeProcInstance( pCb, hInstance );
/* do stuff */
Do_it( ..., fpProc, ...);
/* do more stuff */
FreeProcInstance( fpProc );
ReleaseProc16( pCb );
```

It is not necessary to use this general code in the case of the regular Windows API functions. The following functions will automatically allocate the correct 16-bit/32-bit callback interface functions:

- ChooseColor
- ChooseFont
- CorrectWriting
- CreateDialog
- CreateDialogIndirect
- CreateDialogIndirectParam
- CreateDialogParam
- DdeInitialize
- DialogBox
- DialogBoxIndirect
- DialogBoxIndirectParam
- DialogBoxParam
- DictionarySearch
- EnumChildWindows
- EnumFontFamilies
- EnumFonts
- EnumMetaFile
- EnumObjects
- EnumProps
- EnumSymbols
- EnumTaskWindows
- EnumWindows
- Escape (SETABORTPROC option)
- FindText
- GetOpenFileName
- GetSaveFileName
- GlobalNotify
- GrayString
- LineDDA
- mciSetYieldProc
- mmioInstallIOProc
- NotifyRegister
- PrintDlg

- ProcessWriting
- Recognize
- RecognizeData
- RegisterClass
- ReplaceText
- SetClassLong (GCL\_WNDPROC option)
- SetPenHook
- SetResourceHandler
- SetTimer
- SetWindowLong (GWL\_WNDPROC option)
- SetWindowsHook
- SetWindowsHookEx
- TrainInk

As well, the following functions are covered to provide support for automatic creation of 16-bit callback routines:

- FreeProcInstance
- MakeProcInstance
- UnhookWindowsHook

If you need to get a callback that is not used by one of the above functions, then you must code the general case. Typically, this is required when a DLL needs a callback routine. In modules where this is necessary, you define the macro *NOAUTOPROCS* before you include WINDOWS. H as in the following example.

```
#define NOAUTOPROCS
#include <windows.h>
```

Be careful of the following when using NOAUTOPROCS.

- The call to MakeProcInstance and FreeProcInstance for the callback function occurs in a module with NOAUTOPROCS defined.
- 2. No Windows API functions (listed above) are used in the module with *NOAUTOPROCS* defined. If they are, you must code the general case to use them.

Note that **NOAUTOPROCS** is in effect on a module-to-module basis only.

You can avoid using **NOAUTOPROCS** on a call-by-call basis, if you do the following:

```
#undef <function>
    <function>
    Note: re-defining is only needed if you want to
        use a covered version of the function later on.
#define <function> _Cover_<function>
For example:
```

```
{
#undef SetWindowsHook
#undef MakeProcInstance

FARPROC fp,oldfp;
    CALLBACKPTR cbp;
```

```
cbp = GetProc16( CallbackHook, GETPROC_CALLBACK );
   fp = MakeProcInstance( cbp, hInstance );
    oldfp = SetWindowsHook( WH_CALLWNDPROC, fp );
}
```

This allows you to add general case code in the same module, without having to break the module into two

RegisterClass automatically does a GetProc16 for the callback function, unless the macro NOCOVERRC is specified before including WINDOWS. H as in the following example.

```
#define NOCOVERRC
#include <windows.h>
```

#### 20.5.4.1 Window Sub-classing

Sub-classing a Windows control in the 32-bit environment is straightforward. In fact, the code is identical to the code used in the 16-bit environment. A simple example is:

```
FARPROC fpOldProc;
long FAR PASCAL SubClassProc ( HWND hWnd,
                             unsigned message,
                              WORD wParam,
                              LONG lParam )
     * code for sub-classing here
    return( CallWindowProc( fpOldProc, hWnd, message,
                            wParam, lParam ) );
void SubClassDemo( void )
    HWND
                       hControl;
   FARPROC
                       fp;
    extern HANDLE
                      ProgramInstance;
    /* assume hControl gets created in here */
    fpOldProc = (FARPROC) GetWindowLong( hControl, GWL_WNDPROC );
    fp = MakeProcInstance( SubClassProc, ProgramInstance );
    SetWindowLong( hControl, GWL_WNDPROC, (LONG) fp );
    /* set it back */
    SetWindowLong( hControl, GWL_WNDPROC, (LONG) fpOldProc );
    FreeProcInstance( fp );
```

Note that **SetWindowLong** is covered to recognize **GWL\_WNDPROC** and automatically creates a 16-bit callback for the 32-bit callback. When replacing the callback routine with the original 16-bit routine, the covered version of **SetWindowLong** recognizes that the function is not a 32-bit callback, and so passes the pointer right through to Windows unchanged.

## 20.6 Calling 16-bit DLLs

A 16-bit function in a DLL can be called using the *\_Call16* function. The first argument to *\_Call16* is the address of the 16-bit function. This address is usually obtained by calling *GetProcAddress* with the name of the desired function. The second argument to *\_Call16* is a string identifying the types of the parameters to be passed to the 16-bit function.

# Character Parameter Type c call a 'cdecl' function as opposed to a 'pascal' function (if specified, it must be listed first) b unsigned BYTE w 16-bit WORD d 32-bit DWORD f double precision floating-point p 32-bit flat pointer (converted to 16:16 far pointer)

The 16-bit function must use either the *PASCAL* or *CDECL* calling convention. *PASCAL* calling convention is the default. If the function uses the *CDECL* calling convention, then you must specify the letter "c" as the first character of the argument type string.

Pointer types will automatically be converted from 32-bit near pointers to 16-bit far pointers before the function is invoked. Note that this pointer is only valid over the period of the call; after control returns to the 32-bit application, the 16-bit pointer created by the Supervisor is no longer valid.

The return value from \_Call16 is a DWORD.

```
#include <windows.h>
HANDLE hDrv;
FARPROC lpfn;
int cb;
    if( (hDrv = LoadLibrary ("foo.dll")) < 32 )</pre>
        return FALSE;
    if( !(lpfn = GetProcAddress (hDrv, "ExtDeviceMode")) )
        return FALSE;
     * now, invoke the function
    cb = (WORD) \_Call16(
                                  // address of function
           lpfn,
           "wwdppddw",
                                 // parameter type info
           hwnd,
                                 // parameters ...
           hDrv,
           "POSTSCRIPT PRINTER",
           "LPT1",
           NULL,
           NULL,
           \cap
            );
```

## 20.6.1 Making DLL Calls Transparent

This section gives an example of how to make your source code look as if you are calling the 16-bit DLL directly.

Assume there are 3 functions that you want to call in the 16-bit DLL, with prototypes as follows:

```
HWND FAR PASCAL Initialize( WORD start_code );
BOOL FAR PASCAL DoStuff( HWND win_hld, HDC win_dc );
void FAR PASCAL Finish( void );
```

A fragment from the header file that you would include in your 32-bit application would be as follows:

```
extern FARPROC InitializeAddr;
extern FARPROC DoStuffAddr;
extern FARPROC FinishAddr;
#define Initialize( start_code ) \
  _Call16( InitializeAddr, "w", (WORD)start_code )
#define DoStuff( win_hld, data ) \
  _Call16( DoStuffAddr, "wp", (HWND)win_hld, (LPVOID)data )
#define Finish( void ) _Call16( FinishAddr, "" )
```

The header file fragment gives external references for the function addresses for each function, and sets up macros do a Call16 for each of the functions.

At start up, you would call the following function:

```
* LoadDLL - get DLL ready for 32-bit use
BOOL LoadDLL (void)
{
    HANDLE dll;
    dll = LoadLibrary( "chart.dll" );
    if (dll < 32) return (FALSE);
    InitializeAddr = GetProcAddress( dll, "Initialize" );
    DoStuffAddr = GetProcAddress( dll, "DoStuff" );
    FinishAddr = GetProcAddress( dll, "Finish" );
    return ( TRUE );
}
```

This function loads the 16-bit DLL and gets the addresses for all of the entry points in the DLL. By including the header file with all the macros in it, you can code calls to the DLL functions as if you were calling the functions directly. For example:

```
#include <windows.h>
#include "fragment.h"
char *data = "the data";
void TestDLL( void )
    HWND res;
```

## 20.7 Far Pointer Manipulation

The following C library functions are available for manipulating far data. These are useful when using pointers obtained by *MK\_FP32* and *MK\_LOCAL32*.

Memory manipulation:

- \_fmemccpy
- \_fmemchr
- \_fmemcmp
- \_fmemcpy
- \_fmemicmp
- fmemmove
- \_fmemset

String manipulation:

- fstrcat
- \_fstrchr
- \_fstrcmp
- \_fstrcpy
- $\bullet \_fstrcspn$
- \_fstricmp
- \_fstrlen
- \_fstrlwr
- \_fstrncat
- \_fstrncmp
- \_fstrncpy
- \_fstrnicmp
- \_fstrnset
- \_fstrpbrk
- \_fstrrchr
- \_fstrrev
- \_fstrset
- \_fstrspn
- \_fstrtok
- \_fstrupr

## 20.8 \_ 16 Functions

Every Windows API function that accepts a pointer has a corresponding \_16 function. The \_16 version of the function will not convert any of the pointers that it accepts; it will assume that all pointers are 16-bit far pointers already. This applies to both data and function pointers.

Some sample code demonstrating the use for this is:

```
void ReadEditBuffer( char *fname, HWND hwndEdit )
    int
              file;
    HANDLE
              hText;
    char far *flpData;
    LPSTR
              lpData;
    WORD
              filelen;
     * no error checking is performed; we just
     * assume everything works for this example.
     */
    file = _lopen( fname, 0);
    filelen = _llseek( file, OL, 2 );
    hText = (HANDLE) SendMessage( hwndEdit, EM_GETHANDLE,
                                   0, OL);
    LocalReAlloc( hText, filelen+1, LHND );
    flpData = MK_LOCAL32( LocalLock( hText ) );
    lpData = (LPSTR) MK_FP16( flpB );
    _16_lread( file, lpData, filelen );
    _lclose(file);
}
```

This example reads the contents of a file into the buffer of an edit window. Because the edit window's memory is located in the local heap, which is the Supervisor's heap, the MK\_LOCAL32 function is needed to access the data. The MK\_FP16 macro compresses the 32-bit far pointer into a 16-bit far pointer, which can then be used by the \_16\_lread function.

# **21** Windows 32-Bit Dynamic Link Libraries

## 21.1 Introduction to 32-Bit DLLs

Open Watcom C/C++ allows the creation of 32-bit Dynamic Link Libraries (DLL). In fact, 32-bit DLLs are simpler to write than 16-bit DLLs. A 16-bit DLL runs on the caller's stack, and thus DS != SS. This creates difficulties in the small and medium memory models because near pointers to local variables are different from near pointers to global variables. The 32-bit DLL runs on its own stack, in the usual flat memory space, which eliminates these concerns.

There is a special version of the supervisor, W386DLL.EXT that performs a similar job to WIN386.EXT. However, the 32-bit DLL supervisor is a 16-bit Windows DLL, rather than a 16-bit Windows application. On the first use of the 32-bit DLL, the DLL supervisor loads the 32-bit DLL and invokes the 32-bit initialization routine (the DLL's WinMain routine). The initialization routine declares all entry points (via DefineDLLEntry) and performs any other necessary initialization. An index number in the range 1 to 128 is used to identify all external 32-bit DLL routines. DefineDLLEntry is used to assign an index number to each routine, as well as to identify the arguments.

The DLL supervisor contains a general entry point for Windows applications to call into called Win386LibEntry. It also contains 128 specific entry points called DLL1 to DLL128 which correspond to the entry points established via DefineDLLEntry (the first argument to DefineDLLEntry is an index number in the range 1 to 128). These entry points are FAR PASCAL functions. All applications call into the 32-bit DLL via these entry points. They build the necessary stack frame and switch to the 32-bit DLL's data space.

If you call via Win386LibEntry then you pass the DLL entry point number or index (1 to 128) as the last argument. Win386LibEntry uses this index number to call the appropriate 32-bit DLL routine. From a pseudo-code point of view, the 16-bit supervisor might look like the following:

```
DLL1:: set index=1
    invoke 32bitDLLindirect

DLL2:: set index=2
    invoke 32bitDLLindirect
    .

DLL128:: set index=128
    invoke 32bitDLLindirect

Win386LibEntry::
    set index from index_argument
    invoke 32bitDLLindirect

32bitDLLindirect:
    set up stack frame
    switch to 32-bit data space
    call indirect registration_list[ index ]
    .
    .
    .
```

When you are creating a 32-bit DLL, keep in mind that the entry points you define may be invoked by a 16-bit application as well as a 32-bit application. It is for this reason that all far pointers passed to a 32-bit DLL are 16-bit far pointers. Hence, whenever a pointer is passed as an argument to a 32-bit DLL entry point and you wish to access the data it points to, you must convert the pointer appropriately.

## 21.2 A Sample 32-bit DLL

Let us begin our discussion of DLLs by showing the code for a simple DLL. The source code for these examples is provided in the \WATCOM\SAMPLES\DLL directory. We describe how to compile and link the examples in the section entitled "Creating and Debugging Dynamic Link Libraries" on page 162. The code for this DLL can be compiled with the 16-bit compiler to produce a 16-bit DLL and it can can be compiled with the 32-bit compiler to produce a 32-bit DLL. The example illustrates the fundamental differences between the two types of DLLs. The 32-bit DLL has a WinMain routine and the 16-bit DLL has a LibMain routine.

```
long FAR PASCAL __export FooMe1(WORD w1, DWORD w2, WORD w3)
  char buff[128];
  sprintf( buff, "FooMe1: w1=%hx, w2=%lx, w3=%hx",
           w1, w2, w3);
  MessageBox( NULL, buff, DLL_ID, MB_OK );
  return ( w1 + w2 );
long FAR PASCAL __export FooMe2( DWORD w1, WORD w2 )
  char buff[128];
  sprintf( buff, "FooMe2: w1=%lx, w2=%hx", w1, w2 );
 MessageBox( NULL, buff, DLL_ID, MB_OK );
  return ( w1 + 1 );
}
#if defined(\underline{\phantom{0}}386\underline{\phantom{0}})/* if we are doing a 32-bit DLL */
long PASCAL WinMain ( HANDLE hInstance,
                      HANDLE hPrevInstance,
                      LPSTR lpszCmdLine,
                      int
                             nCmdShow )
  if( DefineDLLEntry( 1, (void *) FooMe1, DLL_WORD,
              DLL_DWORD, DLL_WORD, DLL_ENDLIST )) {
      return(0);
  if ( DefineDLLEntry ( 2, (void *) FooMe2, DLL_DWORD,
               DLL_WORD, DLL_ENDLIST ) ) {
      return(0);
  MessageBox( NULL, "32-bit DLL Started", DLL_ID, MB_OK );
  return(1);
#else
                     /* else we are doing a 16-bit DLL */
BOOL FAR PASCAL LibMain ( HANDLE hInstance,
                          WORD wDataSegment,
                          WORD wHeapSize,
                          LPSTR lpszCmdLine )
  #if 0
    We can't use MessageBox here since static binding is
    used and a message queue has not been created by the
    time DLL16 is loaded.
  MessageBox( NULL, "16-bit DLL Started", DLL_ID, MB_OK );
  #endif
  return ( TRUE );
#endif
```

To create a 16-bit DLL from this code, the following steps must be performed.

#### Example:

```
C>wcc dll /mc /bt=windows /zu /fo=dll16
C>wlink system windows_dll file dll16
C>wlib -n dll16 +dll16.dll
```

To create a 32-bit DLL from this code, the following steps must be performed.

#### Example:

```
C>wcc386 dll /bt=windows /fo=dll32
C>wlink system win386 file dll32
C>wbind -n -d dll32
```

There are two entry points defined, FooMe1 (index number 1) and FooMe2 (index number 2). FooMe1 accepts three arguments: a WORD, a DWORD, and a WORD. FooMe2 accepts two arguments: a DWORD and a WORD.

WinMain returns zero to notify Windows that the DLL initialization failed, and returns a one if initialization succeeds.

WinMain accepts the same arguments as the WinMain procedure of a regular Windows program, however, only two arguments are used. hInstance is the DLL handle and lpszCmdLine is the command line passed to the DLL.

# 21.3 Calling Functions in a 32-bit DLL from a 16-bit Application

The following is a 16-bit Windows program that demonstrates how to call the two routines defined in our DLL example.

#### Example:

```
/*
  * EXE16.C
  */
#include <stdio.h>
#include <windows.h>

#define Add3 1
#define Add2 2

typedef long (FAR PASCAL *FPROC)();
typedef long (FAR PASCAL *FARPROC1)(WORD, DWORD, WORD, int);
typedef long (FAR PASCAL *FARPROC2)(DWORD, WORD, int);
long FAR PASCAL FooMe1( WORD, DWORD, WORD );
long FAR PASCAL FooMe2( DWORD, WORD );
```

```
int PASCAL WinMain ( HANDLE hInstance,
                    HANDLE hPrevInstance,
                    LPSTR lpszCmdLine,
                    int nCmdShow)
 FPROC fp;
  HANDLE hlib;
  long cb;
  char buff[128];
  MessageBox( NULL, "16-bit EXE Started", "EXE16", MB_OK );
  /* Do the 16-bit demo using static binding */
  cb = FooMel(0x666, 0x77777111, 0x6969);
  sprintf( buff, "RC1 = %lx", cb );
  MessageBox( NULL, buff, "EXE16", MB_OK );
  cb = FooMe2(0x12345678, 0x8888);
  sprintf( buff, "RC2 = %lx", cb );
  MessageBox( NULL, buff, "EXE16", MB_OK );
  /* Do the 32-bit demo */
  hlib = LoadLibrary( "dll32.dll" );
  fp = (FPROC) GetProcAddress( hlib, "Win386LibEntry" );
  cb = (*(FARPROC1) fp) (0x666, 0x77777111, 0x6969, Add3);
  sprintf( buff, "RC1 = %lx", cb );
  MessageBox( NULL, buff, "EXE16", MB_OK );
  cb = (*(FARPROC2)fp)(0x12345678, 0x8888, Add2);
  sprintf(buff, "RC2 = %lx", cb);
  MessageBox( NULL, buff, "EXE16", MB_OK );
  return(0);
}
```

Note that the last argument of a call to the 32-bit DLL routine is the index number of the 32-bit DLL routine to use. To create the 16-bit sample Windows executable from this code, the following steps must be performed.

```
Example:
```

```
C>wcc exe16 /bt=windows
C>wlink system windows file exel6 library dll16
```

## 21.4 Writing a 16-bit Cover for the 32-bit DLL

The following is a suggested way to make a 32-bit DLL behave just like a 16-bit DLL from the point of view of the person trying to use the DLL.

Create a library of cover functions for each of the entry points. Each library entry would call the 32-bit DLL using the appropriate index number.

For example, assume we have 3 functions in our DLL, Initialize, DoStuff, and Finish. Assume Initialize takes an integer, DoStuff takes an integer and a pointer, and Finish takes nothing. We could build a 16-bit library as follows:

#### Example:

```
#include <windows.h>
typedef long (FAR PASCAL *FPROC)();
extern long FAR PASCAL Win386LibEntry();
FPROC LibEntry = Win386LibEntry;

BOOL Initialize( int parm )
{
    return( LibEntry( parm, 1 ) );
}

int DoStuff( int parm1, LPVOID parm2 )
{
    return( LibEntry( parm1, parm2, 2 ) );
}

void Finish( void )
{
    LibEntry( 3 );
}
```

## 21.5 Creating and Debugging Dynamic Link Libraries

In the following sections, we will take you through the steps of compiling, linking, and debugging both 16-bit and 32-bit Dynamic Link Libraries (DLLs).

We will use example programs that are provided in source-code form in the Open Watcom C/C++ package. The files described in this chapter are located in the directory  $\MATCOM\SAMPLES\DLL$ . The following files are provided:

GEN16.C	is the source code for a generic 16-bit Windows application that calls functions in a 32-bit Windows DLL.
GEN16.LNK	is the linker directive file for linking the 16-bit Windows application.
GEN32.C	is the source code for a generic 32-bit Windows application that calls functions in both 16-bit and 32-bit Windows DLLs.
GEN32.LNK	is the linker directive file for linking the 32-bit Windows application.
DLL16.C	is the source code for a simple 16-bit DLL containing one library routine.
DLL16.LNK	is the linker directive file for linking the 16-bit Windows DLL.
DLL32.C	is the source code for a more complex 32-bit DLL containing three library routines.
DLL32.LNK	is the linker directive file for linking the 32-bit Windows DLL.

**EXE16.C** is the source code for a generic 16-bit Windows application that calls functions

in both 16-bit and 32-bit Windows DLLs.

**DLL.C** is the source code for a DLL containing three library routines. The source code

for this DLL can be used to create both 16-bit and 32-bit DLLs.

**MAKEFILE** is a makefile for compiling and linking the programs described above.

## 21.5.1 Building the Applications

To create the DLLs and test applications, we will use the WATCOM Open Watcom Make utility and the supplied makefile.

Example:

C>wmake -f makefile

## 21.5.2 Installing the Examples under Windows

Start up Microsoft Windows 3.x if you have not already done so. Add the EXE16.EXE file to one of your Window groups using the Microsoft Program Manager.

- 1. Select the "New..." entry from the "File" menu of the Microsoft Windows Program Manager.
- 2. Select "Program Item" from the "New Program Object" window and press the "OK" button.
- 3. Enter "DLL Test" as a description for the EXE16 program. Enter the full path to the EXE16 program as a command line.

Example:

Description: Test

Command Line: c:\work\dll\exe16.exe

## 21.5.3 Running the Examples

Start the 16-bit application by double clicking on its icon. A number of message boxes are presented. You may wish to compare the output in each message box with the source code of the program to determine if the correct results are being obtained. Click on the "OK" button as each of them are displayed.

## 21.5.4 Debugging a 32-bit DLL

The Open Watcom Debugger can be used to debug a DLL. To debug a 32-bit DLL, a "breakpoint" instruction must be inserted into the source code for the DLL at the "WinMain" entry point. This is done using the "pragma" compiler directive. We have already added the breakpoint to the source code for the 32-bit DLL.

```
Example:
   extern void BreakPoint (void);
   #pragma aux BreakPoint = 0xcc;
   int PASCAL WinMain ( HANDLE hInstance,
                       HANDLE x1,
                        LPSTR lpCmdLine,
                        int x2)
     BreakPoint();
     DefineDLLEntry( 1, (void *) Lib1,
                            DLL_WORD,
                            DLL_DWORD,
                            DLL_WORD,
```

Start up Microsoft Windows 3.x if you have not already done so. Start the debugger by double-clicking on the Open Watcom Debugger icon. At the prompt, enter the path specification for the application. When the debugger has successfully loaded EXE16, start execution of the program. When the breakpoint is encountered in the 32-bit DLL, the debugger is re-entered. The debugger will automatically skip past the breakpoint.

From this point on, you can symbolically debug the 32-bit DLL. You might, for example, set breakpoints at the start of each DLL routine to debug each of them as they are called.

## 21.5.5 Summary

Note that the "WinMain" entry point is only called once, at the start of any application requesting it. After this, the "WinMain" entry point is no longer called. You may have to restart Windows to debug this section of code a second or third time.

# 22 Interfacing Visual Basic and Open Watcom C/C++ DLLs

## 22.1 Introduction to Visual Basic and DLLs

This chapter describes how to interface Microsoft Visual Basic 3.0 applications and 32-bit Dynamic Link Libraries (DLLs) created by Open Watcom C/C++. It describes how to write functions for a 32-bit DLL, how to compile and link them, and how to call these functions from Visual Basic. One of the proposed techniques involves the use of a set of cover functions in a 16-bit DLL so, indirectly, this chapter also describes interfacing to 16-bit DLLs.

It is possible to invoke the Win386LibEntry function (Open Watcom's 32-bit function entry point, described below) directly from Visual Basic. However, this technique limits the arguments that can be passed to a 32-bit DLL. The procedure and problems are explained below.

To work around the problem, a 16-bit DLL can be created, that covers the 32-bit DLL. Within the 16-bit DLL, we will place cover functions that will call the corresponding 32-bit function in the 32-bit DLL. We illustrate the creation of the 16-bit DLL using the 16-bit C compiler in Open Watcom C/C++.

Before we begin our example, there are some important technical issues to consider.

The discussion in this chapter assumes that you, the developer, have a working knowledge of Visual Basic, including how to bring up the general declarations screen, how to create command buttons, and how to associate code with command buttons. You must use Visual Basic 3.0 or later. Visual Basic Version 2.x will not work because of a deficiency in this product regarding the calling of functions in DLLs.

For the purposes of the following discussion, you should have installed both the 16-bit and 32-bit versions of Open Watcom C/C++, as well as version 3.0 or later of Visual Basic. Ensure that the PATH, INCLUDE and WINDOWS\_INCLUDE environment variables are defined to include at least the directories indicated. We have assumed that Open Watcom C/C++ is installed in the c:\watcom directory, and Visual Basic is in the c:\vb directory:

```
set path=c:\watcom\binw;c:\vb;c:\dos;c:\windows
set include=c:\watcom\h
set windows_include=c:\watcom\h\win
```

Open Watcom's 32-bit DLL supervisor contains a general entry point for Windows applications to call into called Win386LibEntry. It also contains 128 specific entry points called DLL1 to DLL128 which correspond to the entry points established via DefineDLLEntry (the first argument to DefineDLLEntry is an index number in the range 1 to 128). All applications call into the 32-bit DLL via these entry points. They build the necessary stack frame and switch to the 32-bit DLL's data space.

If you call via Win386LibEntry then you pass the DLL entry point number or index (1 to 128) as the last argument. Win386LibEntry uses this index number to call the appropriate 32-bit DLL routine.

In many languages and programs (such as C and Microsoft Excel), function calls are very flexible. In other words, a function can be called with different argument types each time. This is generally necessary for calling Win386LibEntry in a 32-bit extended DLL function. The reason is that this function takes the

same arguments as the function being called, as well as the index number of the called function. After the 32-bit flat model has been set up, Win386LibEntry then calls this function. In Visual Basic, once a function is declared as having certain arguments, it cannot be redeclared. For example, suppose we have a declaration as follows:

#### Example:

```
Declare Function Win386LibEntry Lib "c:\path\vbdl132.dll"
=> (ByVal v1 As Integer, ByVal v2 As Long, ByVal
=> v3 As Integer, ByVal I As Integer) As Long
```

(Note: the => means to continue the statement on the same line.) In this example, we could only call a function in any 32-bit extended DLL with a 16-bit integer as the first and third argument, and a 32-bit integer as the second argument. There are three ways to work around this deficiency in Visual Basic:

- 1. Use the Visual Basic "Alias" attribute to declare Win386LibEntry differently for each DLL routine. Reference the different DLL routines using these aliases.
- 2. Use the specific entry point, one of DLL1 through DLL128, corresponding to the DLL routine that you want to call. Each entry point can be described to take different arguments. We can still use the "Alias" attribute to make the link between the name we use in the Visual Basic function and the name in the 32-bit extended DLL. This is the method that we will use in the "Direct Call" technique discussed below. It is simpler to use since it requires one less argument (you don't require the index number).
- 3. Use a method which involves calling functions in a 16-bit "cover" DLL written in a flexible-argument language, which then calls the functions in the 32-bit DLL. This is the "Indirect Call" method discussed below.

## 22.2 A Working Example

The best way to demonstrate these techniques is through an example. This example consists of a Visual Basic application with 3 push buttons. The first push button invokes a direct call to a 32-bit DLL which will display a message window with its arguments, the second push button invokes an indirect call to the same function through a 16-bit DLL, and the third button exits the Visual Basic application.

#### To create a Visual Basic application:

- (1) Start up a new project folder from the "File" menu.
- (2) Select "View Form" from the "Project" window.
- (3) **Draw three command buttons** on the form by selecting command buttons from the "Toolbox" window.
- (4) Change the caption on each button. To do this, highlight the first button. Then, open the "Properties" window. Double click on the "Caption window", and change the caption to "Direct call". Highlight the second button, and change its caption to "Indirect call". Highlight the third, changing the caption to "Exit".

Now, your Visual Basic application should have three push buttons, "Direct call", "Indirect call", and "Exit".

(5) Double click on the "Direct Call" button.

An edit window will pop up. Enter the following code:

```
Sub Command1_Click ()
    Dim var1, var2 As Integer
    Dim varlong, worked As Long
    var1 = 230
    varlong = 215
    var2 = 32
    worked = Add3(var1, varlong, var2)
    Print worked
    worked = Add2(varlong, var2)
    Print worked
End Sub
```

(6) Double click on the "Indirect Call" button.

Another edit window will pop up. Enter the following code:

```
Sub Command2_Click ()
    Dim var1, var2 As Integer
    Dim varlong, worked As Long
    var1 = 230
    varlong = 215
    var2 = 32
    worked = Function1( var1, varlong, var2 )
    Print worked
    worked = Function2( varlong, var2 )
    Print worked
End Sub
```

(7) **Double click on the "Exit" command button** and enter the following code in the pop-up window:

```
Sub Command3_Click ()
    End
End Sub
```

(8) Select "View Code" from the "Project" window. To interface these Visual Basic functions to the DLLs, the following code is needed in the

```
Object: [general] Proc: [declarations]
```

section of the code. This code assumes that VBDLL32.DLL and COVER16.DLL are in the c:\path directory. Modify the pathnames appropriately if this is not the case. (Note: the => means to continue the statement on the same line.)

```
Declare Function Function1 Lib "c:\path\cover16.dll"
=> (ByVal v1 As Integer, ByVal v2 As Long,
=> ByVal v3 As Integer) As Long

Declare Function Function2 Lib "c:\path\cover16.dll"
=> (ByVal v1 As Long, ByVal v2 As Integer) As Long

Declare Function Add3 Lib "c:\path\vbdl132.dll"
=> Alias "DLL1"
=> (ByVal v1 As Integer, ByVal v2 As Long,
=> ByVal v3 As Integer) As Long

Declare Function Add2 Lib "c:\path\vbdl132.dll"
=> Alias "DLL2"
=> (ByVal v1 As Long, ByVal v2 As Integer) As Long
```

Now, when all of the code below is compiled correctly, and the Visual Basic program is run, the "Direct call" button will call the DLL1 and DLL2 functions directly, aliased as the functions Add3 and Add2 respectively. The "Indirect call" button will call the 16-bit DLL, which will then call the 32-bit DLL, for both Function1 and Function2. To run the Visual Basic program, select "Start" from the "Run" menu.

## 22.3 Sample Visual Basic DLL Programs

The sample programs provided below are for a 32-bit DLL, and a 16-bit cover DLL, which will call the two functions contained in the 32-bit DLL.

#### 22.3.1 Source Code for VBDLL32.DLL

```
#pragma off (unreferenced);
int PASCAL WinMain (HANDLE hInstance, HANDLE x1, LPSTR lpCmdLine, int x2)
#pragma on (unreferenced);
 DefineDLLEntry( 1, (void *) Add3, DLL_WORD, DLL_DWORD, DLL_WORD,
                      DLL_ENDLIST );
 DefineDLLEntry( 2, (void *) Add2, DLL_DWORD, DLL_WORD, DLL_ENDLIST );
 return(1);
```

#### 22.3.2 Source code for COVER16.DLL

The functions in this 16-bit DLL will call the functions in the 32-bit DLL, VBDLL32.DLL, shown above, with the appropriate Win386LibEntry call for each function.

```
* COVER16.C
#include <stdio.h>
                        /* required for all Windows applications */
#include <windows.h>
typedef long (FAR PASCAL *FPROC) ();
FPROC DLL_1;
FPROC DLL_2;
long FAR PASCAL __export Function1( short var1,
                                    long var2,
                                    short var3 )
    return( (long) DLL_1( var1, var2, var3 ) );
long FAR PASCAL __export Function2( long var1, short var2 )
    return( (long) DLL_2( var1, var2 ) );
#pragma off (unreferenced);
BOOL FAR PASCAL LibMain ( HANDLE hInstance, WORD wDataSegment,
                         WORD wHeapSize, LPSTR lpszCmdLine )
#pragma on (unreferenced);
   HANDLE hlib;
    /* Do our DLL initialization */
   hlib = LoadLibrary( "vbdll32.dll" );
    if(hlib < 32) {
       MessageBox ( NULL,
                    "Make sure your PATH contains VBDLL32.DLL",
                    "COVER16", MB_OK | MB_ICONEXCLAMATION );
        return( FALSE );
   DLL_1 = (FPROC) GetProcAddress( hlib, "DLL1" );
   DLL_2 = (FPROC) GetProcAddress( hlib, "DLL2" );
    return ( TRUE );
```

### 22.4 Compiling and Linking the Examples

To create the 32-bit DLL VBDLL32.DLL, type the following at the command line (make sure that VBDLL32.c is in your current directory):

```
wcl386 vbdll32 -bt=windows -bd -d2 -l=win386
wbind vbdll32 -d -n
```

To create the 16-bit DLL COVER16.DLL, type the following at the command line (make sure that COVER16. C are in your current directory):

```
wcl cover16 -mc -bt=windows -bd -zu -d2 -l=windows_dll
```

#### Notes:

- The "mc" option selects the compact memory model (small code, big data). The code for 16-bit DLLs must be compiled with one of the big data models.
- The "bd" option indicates that a DLL will be created from the object files.
- The "bt" option selects the "windows" target. This option causes the C or C++ compiler to generate Windows prologue/epilogue code sequences which are required for Microsoft Windows applications. It also causes the compiler to use the WINDOWS INCLUDE environment variable for header file searches. It also causes the compiler to define the macro \_\_\_WINDOWS\_\_ and, for the 32-bit C or C++ compiler only, the macro \_\_\_WINDOWS\_386\_\_.
- The "zu" option is used when compiling 16-bit code that is to be placed in a Dynamic Link Library (DLL) since the SS register points to the stack segment of the calling application upon entry to the function.
- The "d2" option is used to disable optimizations and include debugging information in the object file and DLL. The techniques for debugging DLLs are described in the chapter entitled "Windows 32-Bit Dynamic Link Libraries" on page 157.

You are now ready to run the Visual Basic application.

## 23 WIN386 Library Functions and Macros

Each special Windows function or macro in the Open Watcom C/C++ library is described in this chapter. Each description consists of a number of subsections:

This subsection gives the header files that should be included within a source file that references the function or macro. It also shows an appropriate declaration for the function or for a function that could be substituted for a macro. This declaration is not included in your program; only the header file(s) should be included.

When a pointer argument is passed to a function and that function does not modify the item indicated by that pointer, the argument is shown with const before the argument. For example,

const char \*string

indicates that the array pointed at by string is not changed.

**Description:** This subsection is a description of the function or macro.

**Returns:** This subsection describes the return value (if any) for the function or macro.

**Errors:** This subsection describes the possible errno values.

This optional subsection provides a list of related functions or macros. See Also:

Example: This optional subsection consists of one or more examples of the use of the function. The examples are

often just fragments of code (not complete programs) for illustration purposes.

**Classification:** This subsection provides an indication of where the function or macro is commonly found. The

functions or macros in this section are all classified as "WIN386" (i.e., they pertain to 32-bit Windows

programming).

The AllocAlias16 function is a wide-character version of that operates with wide-character strings. The AllocAlias16 function is a wide-character version of that operates with wide-character strings. Synopsis: #include <windows.h>

DWORD AllocAlias16( void \*ptr );

**Description:** The AllocAlias16 function obtains a 16-bit far pointer equivalent of a 32-bit near pointer. These

pointers are used when passing data pointers to Windows through functions that have DWORD

arguments, and for any pointers within data structures passed this way.

**Returns:** The AllocAlias 16 function returns a 16-bit far pointer usable by Windows, or returns 0 if the alias

cannot be allocated.

See Also: FreeAlias16

Example: #include <windows.h>

```
DWORD mcs_16;
/*
 * Send a message to a MDI client to create a window.
 * 16SendMessage is used for this example, since it will
 * not do any pointer conversions automatically.
 */
MDICREATESTRUCT mcs;
mcs.szTitle = (LPSTR) AllocAlias16( "c:\\foo.bar" );
mcs.szClass = (LPSTR) AllocAlias16( "mdichild" );
mcs.hOwner = hInst;
mcs.x = mcs.cx = (int) CW_USEDEFAULT;
mcs.y = mcs.cy = (int) CW_USEDEFAULT;
mcs.style = 0;
/* tell the MDI Client to create the child */
mcs 16 = AllocAlias16( &mcs );
hwnd = (WORD) _16SendMessage( hwndMDIClient,
                           WM_MDICREATE,
                            (LONG) mcs_16);
FreeAlias16( mcs_16 );
FreeAlias16( (DWORD) mcs.szClass );
FreeAlias16( (DWORD) mcs.szTitle );
```

#### **Classification:** WIN386

The AllocHugeAlias16 function is a wide-character version of that operates with wide-character strings. The AllocHugeAlias16 function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h>

DWORD AllocHugeAlias16 (void \*ptr, DWORD size );

**Description:** The AllocHugeAlias16 function obtains a 16-bit far pointer to a 32-bit memory object that is *size* bytes

in size. This is similar to the function AllocAlias16, except that AllocAlias16 will only give 16-bit far pointers to 32-bit memory objects of up to 64K in size. To get 16-bit far pointers to 32-bit

memory objects larger than 64K, AllocHugeAlias16 should be used.

**Returns:** The AllocHugeAlias16 function returns a 16-bit far pointer usable by Windows, or returns 0 if the alias

cannot be allocated.

See Also: AllocAlias16, FreeAlias16, FreeHugeAlias16

**Example:** #include <windows.h>

#include <malloc.h> #define SIZE 300000

> DWORD alias; void \*tmp;

tmp = malloc( SIZE );

alias = AllocHugeAlias16( tmp, SIZE );

/\* Windows calls using the alias ... \*/

FreeHugeAlias16( alias, SIZE );

#### Classification: WIN386

The \_Call16 function is a wide-character version of that operates with wide-character strings. The \_Call16 function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h>

DWORD \_Call16( FARPROC lpFunc, char \*fmt, ...);

**Description:** 

The \_Call16 function performs the same function as GetIndirectFunctionHandle, InvokeIndirectFunctionHandle and FreeIndirectFunctionHandle but is much easier to use. The first argument lpFunc is the address of the 16-bit function to be called. This address is usually obtained by calling GetProcAddress with the name of the desired function. The second argument fmt is a string identifying the types of the parameters to be passed to the 16-bit function.

Character	Parameter Type
c	call a 'cdecl' function as opposed to a 'pascal' function (if specified, it must be listed first)
$\boldsymbol{b}$	unsigned BYTE
W	16-bit WORD
d	32-bit DWORD
f	double precision floating-point
p	32-bit flat pointer (converted to 16:16 far pointer)

The 16-bit function must use either the PASCAL or CDECL calling convention. PASCAL calling convention is the default. If the function uses the CDECL calling convention, then you must specify the letter "c" as the first character of the argument type string.

Pointer types will automatically be converted from 32-bit near pointers to 16-bit far pointers before the function is invoked. Note that this pointer is only valid over the period of the call; after control returns to the 32-bit application, the 16-bit pointer created by the Supervisor is no longer valid.

**Returns:** The \_Call16 function returns a 32-bit DWORD which represents the return value from the 16-bit

function that was called.

See Also: GetIndirectFunctionHandle, FreeIndirectFunctionHandle

**Example:** 

```
#include <windows.h>
HANDLE hDrv;
FARPROC lpfn;
int cb;
    if( (hDrv = LoadLibrary ("foo.dll")) < 32 )</pre>
        return FALSE;
    if( !(lpfn = GetProcAddress (hDrv, "ExtDeviceMode")) )
        return FALSE;
     * now, invoke the function
     */
    cb = (WORD) \_Call16(
                                 // address of function
           lpfn,
           "wwdppddw",
                                 // parameter type info
           hwnd,
                                 // parameters ...
           hDrv,
           NULL,
           "POSTSCRIPT PRINTER",
           "LPT1",
           NULL,
           NULL,
           0
            );
```

The DefineDLLEntry function is a wide-character version of that operates with wide-character strings. The DefineDLLEntry function is a wide-character version of that operates with wide-character strings. **Synopsis:** #include <windows.h> int DefineDLLEntry( int index, void \* routine, ... );

#### **Description:**

The DefineDLLEntry function defines an *index* number for the 32-bit DLL procedure *routine*. The parameter index defines the index number that must be used in order to invoke the 32-bit FAR procedure routine. The variable argument list defines the types of parameters that will be received by the 32-bit DLL *routine*. Valid parameter types are:

DLL\_PTR 16-bit far pointer DLL\_DWORD 32-bits DLL WORD 16-bits DLL\_CHAR 8-bits DLL ENDLIST Marks the end of the variable argument list.

Note that all pointers are received as 16-bit far pointers. To access the data from the 32-bit DLL, the MK\_FP32 macro must be applied. The data can then be accessed with the resulting 32-bit far pointer.

**Returns:** The DefineDLLEntry function returns zero if successful, and a non-zero value otherwise.

#### **Example:**

```
#include <windows.h>
int FAR PASCAL FooMe ( WORD w1, DWORD w2, WORD w3 )
{
  char str[128];
  sprintf( str, "w1=%hx, w2=%lx, w3=%hx", w1, w2, w3 );
 MessageBox( NULL, str, "DLL Test", MB_OK );
  return ( w1 + w2 );
}
int PASCAL WinMain ( HANDLE hInstance, HANDLE x1,
        LPSTR lpCmdLine, int x2 )
 DefineDLLEntry( 1, (PROCPTR) FooMe, DLL_WORD,
                  DLL_DWORD, DLL_WORD, DLL_ENDLIST );
 MessageBox( NULL, "32-bit DLL Started", "Test", MB_OK );
  return(1);
}
```

#### Classification: WIN386

The DefineUserProc16 function is a wide-character version of that operates with wide-character strings. The DefineUserProc16 function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h> int DefineUserProc16( int typ, PROCPTR routine, ...);

**Description:** 

The DefineUserProc16 function defines the arguments accepted by the user defined callback procedure routine. There may be up to 32 user defined callbacks. The parameter typ indicates which one of GETPROC\_USERDEFINED\_1 through GETPROC\_USERDEFINED\_32 is being defined (see GetProc16). The callback routine must be declared as FAR PASCAL, or as FAR cdecl. The variable argument list defines the types of parameters that will be received by the user defined callback procedure *routine*. Valid parameter types are:

UDP16\_PTR 16-bit far pointer

UDP16 DWORD 32-bits

UDP16\_WORD 16-bits

UDP16\_CHAR 8-bits

UDP16\_CDECL callback routine will be declared as type cdecl rather than as type PASCAL.

This keyword may be placed anywhere before the UDP16\_ENDLIST

keyword.

UDP16\_ENDLIST Marks the end of the variable argument list.

Once the DefineUserProc16 function has been used to declare the user callback routine, then GetProc16 may be used to get a 16-bit function pointer that may be used by Windows.

**Returns:** The DefineUserProc16 function returns zero if it succeeds; and non-zero if it fails.

See Also: GetProc16

**Example:** #include <windows.h>

```
WORD FAR PASCAL Test ( DWORD a, WORD b )
{
  char foo[128];
  sprintf( foo, "a=%lx, b=%hx", a, b );
 MessageBox( NULL, foo, "TEST", MB_OK );
  return( 0x123 );
```

The FreeAlias16 function is a wide-character version of that operates with wide-character strings. The FreeAlias16 function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h> void FreeAlias16( DWORD fp16 );

**Description:** FreeAlias16 frees a 16-bit far pointer alias for a 32-bit near pointer that was allocated with

AllocAlias16. This is important to do when there is no further use for the pointer since there are a

limited number of 16-bit aliases available (due to limited space in the local descriptor table).

**Returns:** The FreeAlias16 function returns nothing.

See Also: AllocAlias16

**Example:** #include <windows.h>

```
DWORD mcs_16;
 * Send a message to a MDI client to create a window.
 * _16SendMessage is used for this example, since it will
 * not do any pointer conversions automatically.
MDICREATESTRUCT mcs;
mcs.szTitle = (LPSTR) AllocAlias16( "c:\\foo.bar" );
mcs.szClass = (LPSTR) AllocAlias16( "mdichild" );
mcs.hOwner = hInst;
mcs.x = mcs.cx = (int) CW_USEDEFAULT;
mcs.y = mcs.cy = (int) CW_USEDEFAULT;
mcs.style = 0;
/* tell the MDI Client to create the child */
mcs_16 = AllocAlias16(\&mcs);
hwnd = (WORD) _16SendMessage( hwndMDIClient,
                           WM_MDICREATE,
                            Ο,
                            (LONG) mcs_16);
FreeAlias16( mcs_16 );
FreeAlias16( (DWORD) mcs.szClass );
FreeAlias16( (DWORD) mcs.szTitle );
```

#### Classification: WIN386

The FreeHugeAlias16 function is a wide-character version of that operates with wide-character strings. The FreeHugeAlias16 function is a wide-character version of that operates with wide-character strings.

Synopsis: #include <windows.h>

void FreeHugeAlias16( DWORD fp16, DWORD size );

**Description:** FreeHugeAlias16 frees a 16-bit far pointer alias that was allocated with AllocHugeAlias16. The

size of the original 32-bit memory object must be specified. It is important to use

FreeHugeAlias16 when there is no further use for the pointer, since there are a limited number of

16-bit aliases available (due to limited space in the local descriptor table).

**Returns:** The FreeHugeAlias16 function returns nothing.

See Also: AllocHugeAlias16, AllocAlias16, FreeAlias16

Example: #include <windows.h>

#include <malloc.h>
#define SIZE 300000

```
DWORD alias;
void *tmp;
tmp = malloc( SIZE );
alias = AllocHugeAlias16( tmp, SIZE );
/* windows calls using the alias ... */
FreeHugeAlias16( alias, SIZE );
```

#### Classification: WIN386

The FreeIndirectFunctionHandle function is a wide-character version of that operates with wide-character strings. The FreeIndirectFunctionHandle function is a wide-character version of that operates with wide-character strings.

```
Synopsis:
            #include <windows.h>
            void FreeIndirectFunctionHandle( HINDIR handle );
Description:
            FreeIndirectFunctionHandle frees a handle that was obtained using
            GetIndirectFunctionHandle. This is important to do when there is no further use for the
            pointer since there are a limited number of 16-bit aliases available (due to limited space in the local
            descriptor table).
Returns:
            The FreeIndirectFunctionHandle function returns nothing.
See Also:
            _Call16, GetIndirectFunctionHandle, InvokeIndirectFunction
Example:
            #include <windows.h>
               HANDLE hDrv;
              FARPROC lpfn;
               if( (hDrv = LoadLibrary( "foo.lib" )) < 32 )</pre>
                   return FALSE;
               if( !(lpfn = GetProcAddress( hDrv, "ExtDeviceMode" )) )
                   return FALSE;
            #ifdef ___WINDOWS_386_
              hIndir = GetIndirectFunctionHandle(
                             lpfn,
                             INDIR_WORD,
                             INDIR_WORD,
                             INDIR DWORD,
                             INDIR_PTR,
                             INDIR_PTR,
                             INDIR_DWORD,
                             INDIR_DWORD,
                             INDIR_WORD,
                             INDIR_ENDLIST );
               cb = (WORD) InvokeIndirectFunction(
                               hIndir,
                               hwnd,
                               hDrv,
                               NULL,
                               "POSTSCRIPT PRINTER",
                               "LPT1",
                               NULL,
                               NULL,
                               0);
              FreeIndirectFunctionHandle( hIndir );
```

```
#else
 cb = lpfn(hwnd,
             hDrv,
             NULL,
             "POSTSCRIPT PRINTER",
             "LPT1",
             NULL,
             NULL,
             0);
#endif
```

The GetIndirectFunctionHandle function is a wide-character version of that operates with  $wide-character\ strings.\ The\ {\tt GetIndirectFunctionHandle}\ function\ is\ a\ wide-character\ version\ of$ that operates with wide-character strings.

**Synopsis:** #include <windows.h>

HINDIR GetIndirectFunctionHandle(FARPROC prc, ...);

**Description:** 

The GetIndirectFunctionHandle function gets a handle for a 16-bit procedure that is to be invoked indirectly. The procedure is assumed to have PASCAL calling convention, unless the INDIR\_CDECL parameter is used, to indicate that Microsoft C calling convention is to be used. The 16-bit far pointer prc is supplied to GetIndirectFunctionHandle, and a list of the type of each parameter (in the order that they will be passed to the 16-bit function). The parameter types are:

INDIR\_DWORD A DWORD will be passed.

INDIR\_WORD A WORD will be passed.

INDIR\_CHAR A char will be passed.

INDIR\_PTR A pointer will be passed. This is only used if pointer conversion from 32-bit

to 16-bit is required, otherwise; INDIR\_DWORD is specified.

INDIR\_CDECL This option may be included anywhere in the list before the

> INDIR\_ENDLIST keyword. When this is used, the calling convention used to invoke the 16-bit function will be the Microsoft C calling convention.

INDIR\_ENDLIST Marks the end of the parameter list.

There is no substitute for this function when compiling for 16-bit Windows. In order to make the code 16-bit Windows compatible, conditional code (based on the \_\_WINDOWS\_386\_\_ macro) should be placed around the GetIndirectFunctionHandle usage (see the example).

This handle is a data structure that was created using the malloc function. To free the handle, just use one of the FreeIndirectFunctionHandle or free functions.

You may find it easier to use \_Call16 rather than GetIndirectFunctionHandle followed by a call to InvokeIndirectFunction.

**Returns:** 

The GetIndirectFunctionHandle function returns a handle to the indirect function, or NULL if a handle could not be allocated. This handle is used in conjunction with InvokeIndirectFunction to call the 16-bit procedure.

See Also: \_Call16, FreeIndirectFunctionHandle, InvokeIndirectFunction

**Example:** #include <windows.h>

```
HANDLE hDrv;
FARPROC lpfn;
if( (hDrv = LoadLibrary( "foo.lib" )) < 32 )</pre>
    return FALSE;
if( !(lpfn = GetProcAddress( hDrv, "ExtDeviceMode" )) )
    return FALSE;
```

```
#ifdef ___WINDOWS_386_
 hIndir = GetIndirectFunctionHandle(
              lpfn,
              INDIR_WORD,
              INDIR_WORD,
              INDIR_DWORD,
              INDIR_PTR,
              INDIR_PTR,
              INDIR_DWORD,
              INDIR_DWORD,
              INDIR_WORD,
              INDIR_ENDLIST );
  cb = (WORD) InvokeIndirectFunction(
                hIndir,
                hwnd,
                hDrv,
                NULL,
                 "POSTSCRIPT PRINTER",
                 "LPT1",
                NULL,
                NULL,
                 0);
 FreeIndirectFunctionHandle( hIndir );
#else
  cb = lpfn(hwnd,
             hDrv,
             NULL,
             "POSTSCRIPT PRINTER",
             "LPT1",
             NULL,
             NULL,
             0);
#endif
```

The GetProc16 function is a wide-character version of that operates with wide-character strings. The GetProc16 function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h>

CALLBACKPTR GetProc16 ( PROCPTR fcn, long type );

**Description:** 

The GetProc16 function returns a 16-bit far function pointer suitable for use as a Windows callback function. This callback function will invoke the 32-bit far procedure specified by fcn. The types of callback functions that may be allocated are:

GETPROC CALLBACK This is the most common form of callback; suitable as the callback routine for a window. The callback has the form:

```
long FAR PASCAL WProc ( HWND, unsigned,
            WORD, LONG );
```

GETPROC\_ABORTPROC This is the callback type used for trapping abort requests when printing. The callback has the form:

```
int FAR PASCAL AbortProc( HDC, WORD );
```

GETPROC ENUMCHILDWINDOWS This callback is used with the EnumChildWindows Windows function. The callback function has the form

```
BOOL FAR PASCAL EnumChildWindowsFunc(
            HWND, DWORD );
```

GETPROC\_ENUMFONTS This callback type is used with the EnumFonts Windows function. The callback has the form:

```
int FAR PASCAL EnumFontsFunc (LPLOGFONT,
            LPTEXTMETRICS, short, LPSTR );
```

GETPROC ENUMMETAFILE This callback is used with the EnumMetaFile Windows function. The callback function has the form:

```
int FAR PASCAL EnumMetaFileFunc( HDC,
            LPHANDLETABLE, LPMETARECORD,
            short, LPSTR );
```

GETPROC\_ENUMOBJECTS This callback is used with the EnumObjects Windows function. The callback function has the form:

```
int FAR PASCAL EnumObjectsFunc( LPSTR, LPSTR );
```

GETPROC ENUMPROPS FIXED DS This callback is used with the EnumProps Windows function, when the fixed data segments callback is needed. The callback function has the form:

```
int FAR PASCAL EnumPropsFunc (
            HWND, LPSTR, HANDLE );
```

GETPROC ENUMPROPS MOVEABLE DS This callback is used with the EnumProps Windows function, when the moveable data segments callback is needed. The callback function has the form:

```
int FAR PASCAL EnumPropsFunc(
            HWND, WORD, PSTR, HANDLE );
```

**GETPROC\_ENUMTASKWINDOWS** This callback is used with the EnumTaskWindows Windows function. The callback function has the form:

GETPROC\_ENUMWINDOWS This callback is used with the EnumWindows Windows function.

The callback function has the form:

```
int FAR PASCAL EnumWindowsFunc ( HWND, DWORD );
```

**GETPROC\_GLOBALNOTIFY** This callback is used with the GlobalNotify Windows function. The callback function has the form:

```
int FAR PASCAL GlobalNotifyFunc ( HANDLE );
```

**GETPROC\_GRAYSTRING** This callback is used with the GrayString Windows function. The callback function has the form:

**GETPROC\_LINEDDA** This callback is used with the LineDDA Windows function. The callback function has the form:

**GETPROC\_SETRESOURCEHANDLER** This callback is used with the SetResourceHandler Windows function. The callback function has the form:

**GETPROC\_SETTIMER** This callback is used with the SetTimer Windows function. The callback function has the form:

**GETPROC\_SETWINDOWSHOOK** This callback is used with the SetWindowsHook Windows function. The callback function has the form:

GETPROC\_USERDEFINED\_x This callback is used in conjunction with DefineUserProc16 function to create a callback routine with an arbitrary set of parameters. Up to 32 user defined callbacks are allowed, they are identified by using GETPROC\_USERDEFINED\_1 through GETPROC\_USERDEFINED\_32. The user defined callback must be declared as a FAR PASCAL function, or as a FAR cdecl function.

**Returns:** 

The GetProc16 function returns a 16-bit far pointer to a callback procedure. This pointer may then be fed to any Windows function that requires a pointer to a function within the 32-bit program. Note that the callback function within the 32-bit program must be declared as FAR.

```
See Also:
           ReleaseProc16
Example:
           #include <windows.h>
             CALLBACKPTR cbp;
             FARPROC lpProcAbout;
              * Get a 16-bit callback routine to point at
              * our About dialogue procedure, then create
              ^{\star} the dialogue. We use _16 versions of
              * MakeProcInstance, DialogBox, and
              * FreeProcInstance because they do not do
              ^{\star} any magic work on the callback routines.
              */
             cbp = GetProc16( (PROCPTR) About,
                               GETPROC_CALLBACK );
             lpProcAbout = _16MakeProcInstance( cbp, hInst );
             _16DialogBox( hInst,
                         "AboutBox",
                         hWnd,
                         lpProcAbout );
             _16FreeProcInstance( lpProcAbout );
             ReleaseProc16( cbp );
```

The InvokeIndirectFunction function is a wide-character version of that operates with wide-character strings. The InvokeIndirectFunction function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h>

long InvokeIndirectFunction( HINDIR handle, ...);

**Description:** The InvokeIndirectFunction function invokes the 16-bit function pointed to by the specified handle.

> $The \ handle \ must \ have \ been \ previously \ allocated \ using \ the \ \texttt{GetIndirectFunctionHandle}$ function. The handle is followed by the list of parameters to be passed to the 16-bit function.

If you specified INDIR\_PTR as a parameter when allocating the handle, then a 16-bit pointer is allocated for a 32-bit pointer that you pass. However, this pointer is freed when the 16-bit function being invoked returns.

There is no substitute for this function when compiling for 16-bit Windows. In order to make the code 16-bit Windows compatible, conditional code (based on the \_\_WINDOWS\_386\_\_ macro) should be placed around the InvokeIndirectFunction usage (see the example).

The InvokeIndirectFunction function returns the value which the 16-bit function returned. If the 16-bit **Returns:** 

function returns a short rather than a long, the result must be typecast.

See Also: \_Call16, FreeIndirectFunctionHandle, GetIndirectFunctionHandle

**Example:** #include <windows.h>

```
HANDLE hDrv;
  FARPROC lpfn;
 HINDIR hIndir;
  int cb;
  if( (hDrv = LoadLibrary( "foo.lib" )) < 32 )</pre>
      return FALSE;
  if( !(lpfn = GetProcAddress( hDrv, "ExtDeviceMode" )) )
      return FALSE;
#ifdef ___WINDOWS_386___
 hIndir = GetIndirectFunctionHandle(
               lpfn,
               INDIR_WORD,
               INDIR_WORD,
               INDIR_DWORD,
               INDIR_PTR,
               INDIR_PTR,
               INDIR_DWORD,
               INDIR_DWORD,
               INDIR_WORD,
               INDIR_ENDLIST );
```

```
cb = (WORD) InvokeIndirectFunction(
                hIndir,
                hwnd,
                hDrv,
                NULL,
                "POSTSCRIPT PRINTER",
                "LPT1",
                NULL,
                NULL,
                0);
 FreeIndirectFunctionHandle( hIndir );
#else
 cb = lpfn( hwnd,
             hDrv,
             NULL,
             "POSTSCRIPT PRINTER",
             "LPT1",
             NULL,
             NULL,
             0);
#endif
```

The MapAliasToFlat function is a wide-character version of that operates with wide-character strings. The MapAliasToFlat function is a wide-character version of that operates with wide-character strings. Synopsis: #include <windows.h>

void \*MapAliasToFlat( DWORD alias );

**Description:** The MapAliasToFlat function returns a 32-bit near pointer equivalent of a pointer allocated previously

with AllocAlias16 or AllocHugeAlias16. This is useful if you are communicating with a

16-bit application that is returning pointers that you previously gave it.

**Returns:** The MapAliasToFlat function returns a 32-bit near pointer usable by the 32-bit application.

See Also: AllocAlias16, AllocHugeAlias16

Example: #include <windows.h>

```
DWORD alias;
void *ptr;

alias = (DWORD) AllocAlias16( &alias );
alias += 5;
ptr = MapAliasToFlat( alias );
if( ptr == ((char *)&alias + 5) ) {
   MessageBox( NULL, "It Worked", "", MB_OK );
} else {
   MessageBox( NULL, "It Failed", "", MB_OK );
}
```

#### Classification: WIN386

The MK\_FP16 function is a wide-character version of that operates with wide-character strings. The MK\_FP16 function is a wide-character version of that operates with wide-character strings.

**Synopsis:** #include <windows.h> DWORD MK\_FP16( void far \* fp32 );

**Description:** The MK\_FP16 function converts a 32-bit far pointer to a 16-bit far pointer. The 16-bit pointer is

created by simply removing the high word of the offset of the 32-bit pointer.

The 32-bit far pointer must be one that was obtained by using MK\_FP32 to extend a 16-bit pointer.

This is useful whenever it is necessary to pass a 16-bit far pointer a parameter to a Windows function

though an \_16 function.

**Returns:** The MK\_FP16 returns a 16-bit far pointer.

See Also: MK\_LOCAL32, MK\_FP32

**Example:** #include <windows.h>

```
DRAWITEMSTRUCT FAR *lpdis;
RECT rc;
DWORD alias;
 ^{\star} The drawitem struct was passed as a long, so we
 * have to convert it to a 32 bit far pointer.
 * Then, we want the 16 bit far pointer of the rcItem
 * element so we can pass it to CopyRect (_16CopyRect
 * is a version of CopyRect that does not convert
 * the pointers it was given).
case WM_DRAWITEM:
  lpdis = MK_FP32( (void *) lParam );
  alias = AllocAlias16( > );
  _16CopyRect((LPRECT) alias,
                (LPRECT) MK_FP16( &lpdis->rcItem ) );
  FreeAlias16( alias );
```

#### Classification: WIN386

The MK\_FP32 function is a wide-character version of that operates with wide-character strings. The MK\_FP32 function is a wide-character version of that operates with wide-character strings.

```
Synopsis:
            #include <windows.h>
            void far *MK_FP32( void * fp16 );
Description:
            The MK_FP32 function converts a 16-bit far pointer to a 32-bit far pointer. This is needed whenever
            Windows returns a 16-bit far pointer, and access to the data is needed by the 32-bit program.
Returns:
            The MK_FP32 returns a 32-bit far pointer.
See Also:
            MK_LOCAL32, MK_FP16
Example:
            #include <windows.h>
              MEASUREITEMSTRUCT far *mis;
               case WM_MEASUREITEM:
                  * Windows has passed us a 16 bit far pointer
                  ^{\star} to the measure item data structure. We
                  * use MK\_FP32 to make that pointer a 32-bit far
                  * pointer, which enables us to access the data.
                 mis = MK_FP32((void *) lParam);
                 mis->itemHeight = MEASUREITEMHEIGHT;
                 mis->itemWidth = MEASUREITEMWIDTH;
                 return TRUE;
```

The MK\_LOCAL32 function is a wide-character version of that operates with wide-character strings. The MK\_LOCAL32 function is a wide-character version of that operates with wide-character strings.

```
Synopsis:
           #include <windows.h>
           void far *MK_LOCAL32( void * fp16 );
```

**Description:** The MK\_LOCAL32 function converts a 16-bit near pointer to a 32-bit far pointer. This is needed

whenever Windows returns a 16-bit near pointer that is to be accessed by the 32-bit program.

**Returns:** The MK\_LOCAL32 returns a 32-bit far pointer.

```
See Also:
             MK_FP32, MK_FP16
```

```
Example:
            #include <windows.h>
```

```
WORD ich, cch;
char *pch;
char far *fpch;
HANDLE hT;
 * Request the data from an edit window; copy it
 \star into a local buffer so that it can be passed
 * to TextOut
 */
ich = (WORD) SendMessage( hwndEdit,
                           EM_LINEINDEX,
                           iLine,
                           OL );
cch = (WORD) SendMessage( hwndEdit,
                           EM_LINELENGTH,
                           ich,
                           OL );
fpch = MK_LOCAL32( LocalLock( hT ) );
pch = alloca( cch );
_fmemcpy( pch, fpch + ich, cch );
TextOut( hdc, 0, yExtSoFar, (LPSTR) pch, cch );
LocalUnlock( hT );
```

#### Classification: WIN386

The PASS\_WORD\_AS\_POINTER function is a wide-character version of that operates with wide-character strings. The PASS\_WORD\_AS\_POINTER function is a wide-character version of that operates with wide-character strings.

#### PASS WORD AS POINTER

Synopsis: #include <windows.h>

void \*PASS\_WORD\_AS\_POINTER( DWORD dw );

**Description:** Some Windows API functions have pointer parameters that do not always take pointers. Sometimes

these parameters are pure data. In order to stop the supervisor from trying to convert the data into a

16-bit far pointer, the PASS\_WORD\_AS\_POINTER function is used.

**Returns:** The PASS\_WORD\_AS\_POINTER returns a 32-bit "near" pointer, that is really the parameter dw.

Example: #include <windows.h>

Func( PASS\_WORD\_AS\_POINTER( 1 ) );

#### **Classification:** WIN386

The ReleaseProc16 function is a wide-character version of that operates with wide-character strings. The ReleaseProc16 function is a wide-character version of that operates with wide-character strings.

```
Synopsis:
           #include <windows.h>
           void ReleaseProc16( CALLBACKPTR cbp );
```

**Description:** ReleaseProc16 releases the callback function allocated by GetProc16. Since the callback routines are

a limited resource, it is important to release the routines when they are no longer required.

**Returns:** The ReleaseProc16 function returns nothing.

See Also: GetProc16

```
Example:
           #include <windows.h>
             CALLBACKPTR cbp;
             FARPROC lpProcAbout;
              * Get a 16-bit callback routine to point at
              * our About dialogue procedure, then create
              ^{\star} the dialogue. We use _16 versions of
              * MakeProcInstance, DialogBox, and
              * FreeProcInstance because they do not do
              * any magic work on the callback routines.
              */
              cbp = GetProc16( (PROCPTR) About,
                                GETPROC_CALLBACK );
              lpProcAbout = _16MakeProcInstance( cbp, hInst );
              _16DialogBox( hInst,
                          "AboutBox",
                          hWnd,
                          lpProcAbout );
```

\_16FreeProcInstance( lpProcAbout );

ReleaseProc16( cbp );

Classification: WIN386

# **24** 32-bit Extended Windows Application Development

The purpose of this chapter is to anticipate some common questions about 32-bit Windows application development.

The following topics are discussed in this chapter:

- Can you call 16-bit code from a 32-bit code?
- Can I WinExec another Windows application?
- How do I add my Windows resources?
- What size of function pointers passed to Windows?
- Why are 32-bit callback routines FAR?
- Why use the 16 API functions?
- What about pointers in structures?
- When do I use MK\_FP32?
- What is the difference between AllocAlias16 and MK\_FP16?

### 24.1 Can you call 16-bit code from a 32-bit code?

A 32-bit Windows application can make a call to 16-bit code through the use of the Open Watcom \_Call16 or InvokeIndirectFunction procedures. These functions ensure that the Open Watcom Windows Supervisor prepares the stack for the 16-bit call and return to the 32-bit code. The 32-bit application uses LoadLibrary function to bring the 16-bit DLL into memory and then calls the 16-bit procedures. To invoke 16-bit procedures, use GetProcAddress to get the 16-bit far pointer to the function. Use the \_Call16 procedure to call the 16-bit function since it is simpler to use than the GetIndirectFunctionHandle, InvokeIndirectFunction, and FreeIndirectFunctionHandle sequence. An example of this process is provided under the \_Call16 Windows library function description.

This method can be used to call any 16-bit Dynamic Link Library (DLL) procedure or any 32-bit extended DLL procedure from within a 32-bit application, including DLLs that are available as products through Independent Software Vendors (ISVs).

### 24.2 Can I WinExec another Windows application?

As far as Windows is concerned, the WinExec was made by a 16-bit application, and the application specified will be started. This new application can be a 16-bit application or another 32-bit application that was implemented with Open Watcom C/C++

### 24.3 How do I add my Windows resources?

The WBIND utility automatically runs the resource compiler to add the resources to the 32-bit Windows supervisor (since the supervisor is a 16-bit Windows application). Note that resource compiler options may be specified by using the "R" option of WBIND.

### 24.4 What size of function pointers passed to Windows?

All function pointers passed to Windows must be 16-bit far pointers since no translation is applied to any function pointers passed to Windows. Translation is often not possible, since any functions that Windows is to call back must be exported, and only 16-bit functions can be exported.

A 16-bit far pointer to a function is obtained in one of two ways: either Windows gives it to you (via GetProcAddr, for example), or you obtain a pointer from the supervisor, via GetProc16.

Function pointers obtained from Windows may either be fed into other Windows functions requiring function pointers, or called indirectly by using \_Call16 or by using the GetIndirectFunctionHandle, InvokeIndirectFunction, and FreeIndirectFunctionHandle sequence.

The function GetProc16 returns a 16-bit far pointer to a callback function that Windows can use. This callback function will direct control into the desired 32-bit routine.

### 24.5 Why are 32-bit callback routines FAR?

The callback routines are declared as FAR so that the compiler will generate a far return from the procedure. This is necessary since the 32-bit callback routine is "far" called from the supervisor.

The callback routine is still "near" in the sense that it lies within the 32-bit flat address space of the application. This means that GetProc16 only needs the offset of the 32-bit callback function in order to set up the 16-bit procedure to call back correctly. Thus, GetProc16 accepts type PROCPTR which is in fact only 4 bytes long. The compiler will provide the offset only, which is, as already stated, all that is needed.

### 24.6 Why use the \_16 API functions?

The regular Windows API functions used in Open Watcom C/C++ automatically convert any pointers to 16-bit far pointers for use by Windows. Sometimes, you may have a set of pointers that are 16-bit far pointers already (e.g., obtained from GlobalLock), and do not need any conversion. The "\_16..." API functions do not convert pointers, they simply pass them on directly to Windows. See the appendix entitled "Special Windows API Functions" on page 205 for a list of the "\_16..." API functions.

### 24.7 What about pointers in structures?

Pointers in structures will be converted if the Windows API function actually takes a pointer to that structure (i.e., if it is possible for the supervisor to identify that structure). There are few functions that accept pointers to structures containing pointers. One such function is RegisterClass which accepts a pointer to a WNDCLASS structure.

If Windows has you passing a pointer to a structure through a 32-bit integer argument, then it is not possible for the supervisor to identify that as a pointer that needs conversion. It is also not possible for the supervisor to convert any pointers contained in the structure, since it is not aware that it is a structure (as far as the supervisor is concerned, that data is what Windows said it was - a 32-bit integer). In this case, it is necessary to get 16-bit far pointer equivalents to the 32-bit near pointers that you want to pass. Use AllocAlias16 for this.

### 24.8 When do I use MK FP32?

MK\_FP32 is used to convert all 16-bit far pointers to 32-bit far pointers that can be used by your 32-bit application. For example, to access the memory returned by GlobalLock requires the use of MK\_FP32. To access any pointer passed to you (in a callback routine) requires the use of MK\_FP32 if you want access to that data in your 32-bit application.

### 24.9 What is the difference between AllocAlias16 and **MK\_FP16?**

AllocAlias16 actually gets a new selector that points at the same memory as the 32-bit near pointer, whereas MK\_FP16 squishes a 32-bit far pointer back into a 16-bit far pointer (i.e., it reverses MK\_FP32).

### 24.10 Tell Me More About Thunking and Aliases

Consider the following example.

```
dwAlias = AllocAlias16( pszSomething );
hwnd = CreateWindowEx(
           0L,
                                  // extendedStyle
            "classname",
                                  // class name
           WS_POPUP | WS_VISIBLE | WS_CLIPSIBLINGS | WS_HSCROLL |
           WS_BORDER | WS_CAPTION | WS_SYSMENU,
           x, y, 0, 0, // x, y, cx, cy
                                 // hwndParent
           hwndParent,
           g_app.hinst,
                                  // control ID
                                  // hInstance
            (void FAR*)dwAlias); // lpCreateParams
FreeAlias16( dwAlias );
```

When I get the lpCreateParams parameter in WM\_CREATE, I don't get the original dwAlias but something else which looks like another alias to me. So the question is: Must the CreateWindowEx parameter lpCreateParams be "thunked" or is this done automatically by the supervisor?

Thunks are always created for function pointers. Aliases are always created for data pointers. There are 3 data pointer parameters in the CreateWindowEx function call. Aliases are created for all three pointers. The lpCreateParams argument is a pointer to a struct which contains 3 pointers. Aliases are not created for the 3 pointers inside the struct. If you need to have this done, then you will have to create the aliases yourself. If you create aliases for the parameters to CreateWindowEx, then you must call the \_16CreateWindowEx function which will not create any aliases.

Here is some further information on thunks (which are created for function pointers). There is code in the supervisor that trys (note the word trys) to determine if the user has already created a thunk and, if so, avoids creating a double thunk which will always generate a GPF. The best policy is to let the supervisor automatically create all thunks for you unless you have a very specific reason not to, in which case you should call the 16 version of the function.

Here is some further information on aliases (which are created for data pointers). There is no way for the supervisor to determine if a value is a 32-bit flat pointer or an alias for the pointer. So if you pass in an alias to the non \_16 version of the function, the supervisor will create an alias for the alias which will end up pointing to the wrong memory location. If you are going to create the alias, then you must call the \_16 version of the function.

# 25 Special Variables for Windows Programming

A000	A selector for addressing the real-mode segment 0xA000.
B000	A selector for addressing the real-mode segment 0xB000.
B800	A selector for addressing the real-mode segment 0xB800.
C000	A selector for addressing the real-mode segment 0xC000.
D000	A selector for addressing the real-mode segment 0xD000.
E000	A selector for addressing the real-mode segment 0xE000.
F000	A selector for addressing the real-mode segment 0xF000.
LocalPtr	The selector for the supervisor's data area.

# **26** Definitions of Windows Terms

CALLBACKPTRPointer to a 16-bit callback routine; used to call into 32-bit functions.

**DWORD** An unsigned long.

**HINDIR** A handle to 16-bit function that needs to be called indirectly.

**PROCPTR** A pointer to a 32-bit callback routine. Although the callback routine is declared

as far, only the 32-bit offset is used.

**WORD** An unsigned short.

## 27 Special Windows API Functions

On rare occasions, you want to use 16-bit far pointers directly in a Windows function. Since all Windows functions in the 32-bit environment are expecting 32-bit near pointers, you cannot simply use the 16-bit far pointer directly in the function.

The following functions are special versions of Windows API functions that do NOT convert any of the pointers from 32-bit to 16-bit. There are \_16 versions of all Windows API functions that accept data pointers.

- 16AddAtom
- \_16AddFontResource
- \_16AdjustWindowRect
- \_16AdjustWindowRectEx
- \_16AnimatePalette
- 16AnsiLower
- \_16AnsiLowerBuff
- \_16AnsiToOem
- \_16AnsiToOemBuff
- \_16AnsiUpper
- \_16AnsiUpperBuff
- \_16BuildCommDCB
- \_16CallMsgFilter
- \_16ChangeMenu
- \_16ClientToScreen
- \_16ClipCursor
- \_16CopyMetaFile
- \_16CopyRect
- \_16CreateBitmap
- \_16CreateBitmapIndirect
- \_16CreateBrushIndirect
- \_16CreateCursor
- 16CreateDC
- \_16CreateDialog
- $\_16 Create Dialog Indirect$
- \_16CreateDialogIndirectParam
- \_16CreateDialogParam
- \_16CreateDIBitmap
- \_16CreateEllipticRgnIndirect
- 16CreateFont
- \_16CreateFontIndirect
- \_16CreateIC
- 16CreateIcon
- 16CreateMetaFile
- \_16CreatePalette
- $\_16 Create Pen Indirect$
- \_16CreatePolygonRgn
- \_16CreatePolyPolygonRgn
- \_16CreateRectRgnIndirect

- 16CreateWindow
- \_16CreateWindowEx
- \_16DialogBox
- \_16DialogBoxIndirect
- \_16DialogBoxIndirectParam
- \_16DialogBoxParam
- \_16DispatchMessage
- \_16DlgDirList
- $\_16 Dlg Dir List Combo Box$
- \_16DlgDirSelect
- \_16DlgDirSelectComboBox
- \_16DPtoLP
- \_16DrawFocusRect
- 16DrawText
- \_16EndPaint
- \_16EnumChildWindows
- \_16EnumFonts
- \_16EnumMetaFile
- \_16EnumObjects
- $\_16EnumProps$
- \_16EnumTaskWindows
- \_16EnumWindows
- \_16EqualRect
- \_16Escape
- \_16ExtTextOut
- \_16FillRect
- \_16FindAtom
- \_16FindResource
- \_16FindWindow
- \_16FrameRect
- \_16FreeProcInstance
- \_16GetAtomName
- \_16GetBitmapBits
- \_16GetCaretPos
- $\_16 Get Char Width$
- \_16GetClassInfo
- \_16GetClassName
- \_16GetClientRect
- 16GetClipboardFormatName
- \_16GetClipBox
- \_16GetCodeInfo
- $\_16GetCommError$
- 16GetCommState
- 16GetCursorPos
- \_16GetDIBits
- \_16GetDlgItemInt
- \_16GetDlgItemText
- \_16GetEnvironment
- \_16GetKeyboardState
- \_16GetKeyNameText
- \_16GetMenuString
- \_16GetMetaFile
- \_16GetModuleFileName
- \_16GetModuleHandle

- 16GetObject
- \_16GetPaletteEntries
- 16GetPriorityClipboardFormat
- \_16GetPrivateProfileInt
- \_16GetPrivateProfileString
- \_16GetProcAddress
- 16GetProfileInt
- \_16GetProfileString
- \_16GetProp
- \_16GetRgnBox
- \_16GetScrollRange
- \_16GetSystemDirectory
- \_16GetSystemPaletteEntries
- 16GetTabbedTextExtent
- \_16GetTempFileName
- $\_16GetTextExtent$
- \_16GetTextFace
- \_16GetTextMetrics
- $\_16 Get Up date Rect$
- $\_16 Get Window Rect$
- \_16GetWindowsDirectory
- \_16GetWindowText
- $\_16GlobalAddAtom$
- $\_16 Global Find Atom$
- \_16GlobalGetAtomName
- \_16GlobalNotify
- \_16GrayString
- \_16InflateRect
- \_16IntersectRect
- \_16InvalidateRect
- \_16InvertRect
- \_16IsDialogMessage
- \_16IsRectEmpty
- \_16LineDDA
- \_16LoadAccelerators
- \_16LoadBitmap
- \_16LoadCursor
- \_16LoadIcon
- 16LoadLibrary
- \_16LoadMenu
- \_16LoadMenuIndirect
- \_16LoadModule
- \_16LoadString
- 16LPtoDP
- \_16MakeProcInstance
- \_16MapDialogRect
- \_16MessageBox
- \_16OemToAnsi
- \_16OemToAnsiBuff
- \_16OffsetRect
- \_16OpenComm
- \_16OpenFile
- \_16OutputDebugString
- \_16PlayMetaFileRecord

- \_16Polygon
- \_16Polyline
- \_16PolyPolygon
- \_16PtInRect
- \_16ReadComm
- \_16RectInRegion
- 16RectVisible
- \_16RegisterClipboardFormat
- $\_16 Register Window Message$
- \_16RemoveFontResource
- \_16RemoveProp
- \_16ScreenToClient
- \_16ScrollDC
- \_16ScrollWindow
- \_16SetBitmapBits
- $\_16 Set Comm State$
- \_16SetDIBits
- \_16SetDIBitsToDevice
- $\_16SetDlgItemText$
- \_16SetEnvironment
- \_16SetKeyboardState
- \_16SetPaletteEntries
- \_16SetProp
- \_16SetRect
- \_16SetRectEmpty
- $\_16 Set Resource Handler$
- $\_16 Set Sys Colors$
- \_16SetTimer
- \_16SetWindowsHook
- $\_16 Set Window Text \\$
- $\_16 Stretch DIBits$
- \_16TabbedTextOut
- 16TextOut
- \_16ToAscii
- \_16TrackPopupMenu
- \_16TranslateAccelerator
- $\_16 Translate MDIS ys Accel$
- \_16TranslateMessage
- 16UnhookWindowsHook
- \_16UnionRect
- $\_16 Unregister Class$
- \_16ValidateRect
- \_16WinExec
- \_16WinHelp
- \_16WriteComm
- \_16WritePrivateProfileString
- \_16WriteProfileString
- \_16\_lread
- \_16\_lwrite

# Windows NT Programming Guide

## **28** Windows NT Programming Overview

Windows NT supports both non-windowed character-mode applications and windowed Graphical User Interface (GUI) applications. In addition, Windows NT supports Dynamic Link Libraries and applications with multiple threads of execution.

We have supplied all the necessary tools for native development on Windows NT. You can also cross develop for Windows NT using either the DOS-hosted compilers and tools, the Windows 95-hosted compilers and tools, or the OS/2-hosted compilers and tools.

Note - If you are on the host with operating system other then 32-bit Windows, you should setup INCLUDE environment variable correctly to compile for 32-bit Windows target.

You can do that by command (DOS, OS/2, Windows 3.x)

set INCLUDE=%WATCOM%\h;%WATCOM%\h\nt

or by command (LINUX)

export INCLUDE=\$WATCOM/h:\$WATCOM/h/nt

Testing and debugging of your Windows NT application must be done on Windows NT or Windows 95.

If you are creating a character-mode application, you may also be interested in a special DOS extender from Phar Lap (TNT) that can run your Windows NT character-mode application under DOS.

## 28.1 Windows NT Programming Note

When doing Win32 programming, you should use the /ei and /zp4 options to compile C and C++ code with the Open Watcom compilers since this adjusts the compilers to match the default Microsoft compiler behaviour. Some Microsoft software relies on the default behaviour of their own compiler regarding the treatment of enums and structure packing alignment.

### 28.2 Windows NT Character-mode Versus GUI

Basically, there are two classes of C/C++ applications that can run in a windowed environment like Windows NT.

The first are those C/C++ applications that do not use any of the Win32 API functions; they are strictly C/C++ applications that do not rely on the features of a particular operating system.

• This Application must be created as Windows NT Character-mode Application.

### Windows NT Programming Guide

The second class of C/C++ applications are those that actually call Win32 API functions directly. These are applications that have been tailored for the Win32 operating environment. There can occure two application types.

- First one uses GUI interface then it must be created as Windows NT GUI Application.
- Second one uses only character console (no GUI) then it must be created as Windows NT Character-mode Application

A subsequent chapters deal with the creation of different application types for Windows NT target.

## 29 Creating Windows NT GUI Applications

This chapter describes how to compile and link Windows NT GUI applications simply and quickly. In this chapter, we look at applications written to exploit the Windows NT Application Programming Interface (API).

We will illustrate the steps to creating Windows NT GUI applications by taking a small sample application and showing you how to compile, link, run and debug it.

## 29.1 The Sample GUI Application

To demonstrate the creation of Windows NT GUI applications, we introduce a simple sample program. The following example is the "hello" program adapted for Windows.

```
#include <windows.h>
int PASCAL WinMain ( HANDLE hInstance, HANDLE hPrevInst,
                    LPSTR lpCmdLine, int nCmdShow)
    MessageBox ( NULL, "Hello world",
                "Open Watcom C/C++ for Windows",
                MB_OK | MB_TASKMODAL );
    return(0);
}
```

The goal of this program is to display the message "Hello world" on the screen. The MessageBox Windows API function is used to accomplish this task. We will take you through the steps necessary to produce this result.

## 29.2 Building and Running the GUI Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl386 -l=nt_win -bt=nt hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=nt win -bt=nt hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bt=nt
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 41
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows NT windowed executable
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries).

The resultant Windows NT GUI application HELLO.EXE can now be run under Windows NT.

## 29.3 Debugging the GUI Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL386 command, this is fairly straightforward. WCL386 recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl386 -l=nt win -bt=nt -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=nt win -bt=nt -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bt=nt -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 66
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows NT windowed executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL386 will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, select the Open Watcom Debugger icon. It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.

## 30 Creating Windows NT Character-mode **Applications**

This chapter describes how to compile and link Windows NT Character-mode applications simply and quickly. In this chapter, we look at applications written to exploit the Windows NT Application Programming Interface (API).

We will illustrate the steps to creating Windows NT Character-mode applications by taking a small sample application and showing you how to compile, link, run and debug it.

## 30.1 The Sample Character-mode Application

To demonstrate the creation of Windows NT Character-mode applications, we introduce a simple sample program. The following example is the "hello" program adapted for Windows.

```
#include <stdio.h>
void main()
    printf( "Hello world\n" );
```

The goal of this program is to display the message "Hello world" on the screen. The C library printf routine is used to accomplish this task. We will take you through the steps necessary to produce this result.

## 30.2 Building and Running the Character-mode Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
C>wcl386 -l=nt -bt=nt hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=nt -bt=nt hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bt=nt
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 41
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows NT Character-mode executable
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries).

The resultant Windows NT Character-mode application HELLO. EXE can now be run under Windows NT.

## 30.3 Debugging the Character-mode Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL386 command, this is fairly straightforward. WCL386 recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
C>wcl386 -l=nt -bt=nt -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
C>wcl386 -l=nt -bt=nt -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -bt=nt -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 10 lines, included 6500, 0 warnings, 0 errors
Code size: 66
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating a Windows NT Character-mode executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL386 will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, select the Open Watcom Debugger icon. It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled *Open Watcom Debugger User's Guide*.

## 31 Windows NT Multi-threaded Applications

This chapter describes how to create multi-threaded applications. A multi-threaded application is one whose tasks are divided among several threads of execution. A process is an executing application and the resources it uses. A thread is the smallest unit of execution within a process. Each thread has its own stack and a set of machine registers and shares all resources with its parent process. The path of execution of one thread does not affect that of another; each thread is an independent entity.

Typically, an application has a single thread of execution. In this type of application, all tasks, once initiated, are completed before the next task begins. In contrast, tasks in a multi-threaded application can be performed concurrently since more than one thread is executing at once. For example, each thread may be designed to perform a separate task.

## 31.1 Programming Considerations

Since a multi-threaded application consists of many threads of execution, there are a number of issues that you must consider.

Since threads share the resources of its parent, it may be necessary to serialize access to these resources. For example, if your application has a function that displays information on the console and is used by all threads, it is necessary to allow only one thread to use that function at any time. That is, once a thread calls that function, the function should ensure that no other thread displays information until all information for the initial thread has been displayed. An example of such a function is the printf library function.

Another issue that must be considered when creating multi-threaded applications is global variables. If you have global variables that contain thread-specific information, there must be an instance of each global variable for each thread. An example of such a variable is the errno global variable defined in the run-time libraries. If an error condition was created by a thread, you would not want it to affect the execution of other threads. Therefore, each thread should contain its own instance of this variable.

## 31.2 Creating Threads

Each application initially contains a single thread. The run-time libraries contain two functions that create and terminate threads of execution. The function \_beginthread creates a thread of execution and the function \_endthread ends a thread of execution. The macro \_threadid can be used to determine the current thread identifier.

**WARNING!** If any thread calls a library function, you must use the \_beginthread function to create the thread. Do not use the CreateThread API function.

### 31.2.1 Creating a New Thread

The \_beginthread function creates a new thread. It is defined as follows.

where description
start\_address is the address of the function that will be called when the newly created thread is executed. When the thread returns from that function, the thread will be terminated. Note that a call to the \_endthread function will also terminate the thread.
stack\_size specifies the size of the stack to be allocated by the operating system for the new thread. The stack size should be a multiple of 4K.
arglist is passed as an argument to the function specified by start\_address. If no argument is required, a value of NULL can be specified.

If a new thread is successfully created, the thread identifier of the new thread is returned. Otherwise, a value of -1 is returned.

The header file process.h contains the definition of the \_beginthread function.

Another thread related function for Windows NT is \_beginthreadex. See the *Open Watcom C Library Reference* for more information.

#### 31.2.2 Terminating the Current Thread

The \_endthread function terminates the current thread. It is defined as follows.

```
void _endthread( void )
```

The header file process.h contains the definition of the \_endthread function.

### 31.2.3 Getting the Current Thread Identifier

The \_threadid macro can be used to determine the current thread identifier. It is defined as follows.

```
int *__threadid(void);
#define _threadid((__threadid()))
```

The header file stddef.h contains the definition of the \_threadid macro.

### 31.3 A Multi-threaded Example

Let us create a simple multi-threaded application.

```
#include <process.h>
#include <stdio.h>
#include <stddef.h>
#include <windows.h>
static volatile int NumThreads;
static volatile int
                       HoldThreads;
CRITICAL_SECTION CriticalSection;
#define NUM_THREADS
#define STACK_SIZE
                       8192
static void a_thread( void *arglist )
   while( HoldThreads ) {
        Sleep(1);
   printf( "Hi from thread %d\n", *_threadid );
    EnterCriticalSection( &CriticalSection );
    --NumThreads:
   LeaveCriticalSection( &CriticalSection );
    _endthread();
int main ( void )
/*********
{
                i;
    printf( "Initial thread id = %d\n", *_threadid );
    NumThreads = 0;
    HoldThreads = 1;
    InitializeCriticalSection( &CriticalSection );
    /* initial thread counts as 1 */
    for( i = 2; i <= NUM_THREADS; ++i ) {</pre>
        if( _beginthread( a_thread, STACK_SIZE, NULL ) == -1 ) {
            printf( "creation of thread %d failed\n", i );
        } else {
            ++NumThreads;
    HoldThreads = 0;
    while( NumThreads != 0 ) {
        Sleep(1);
    DeleteCriticalSection( &CriticalSection );
   return(0);
```

Note:

In the function a\_thread, EnterCriticalSection and LeaveCriticalSection are called when we modify the variable NumThreads. This ensures that the action of extracting the value of NumThreads from memory, incrementing the value, and storing the new result into memory, occurs without interruption. If these functions were not called, it would be possible for two threads to extract the value of NumThreads from memory before an update occurred.

Let us assume that the file mthread.c contains the above example. Before compiling the file, make sure that the WATCOM environment variable is set to the directory in which you installed Open Watcom

C/C++. Also, the **INCLUDE** environment variable must include the \watcom\h\nt and \watcom\h directories ("\WATCOM" is the directory in which Open Watcom C/C++ was installed).

We can now compile and link the application by issuing the following command.

```
C:\>wcl386 -bt=nt -bm -l=nt mthread
```

The "bm" option must be specified since we are creating a multi-threaded application. If your multi-threaded application contains more than one module, each module must be compiled using the "bm" switch.

The "I" option specifies the target system for which the application is to be linked. The system name nt is defined in the file wlsystem.lnk which is located in the "BINW" subdirectory of the directory in which you installed Open Watcom C/C++.

The multi-threaded application is now ready to be run.

## 32 Windows NT Dynamic Link Libraries

A dynamic link library, like a standard library, is a library of functions. When an application uses functions from a standard library, the library functions referenced by the application become part of the executable module. This form of linking is called static linking. When an application uses functions from a dynamic link library, the library functions referenced by the application are not included in the executable module. Instead, the executable module contains references to these functions which are resolved when the application is loaded. This form of linking is called dynamic linking.

Let us consider some of the advantages of using dynamic link libraries over standard libraries.

- Functions in dynamic link libraries are not linked into your program. Only references to the functions in dynamic link libraries are placed in the program module. These references are called import definitions. As a result, the linking time is reduced and disk space is saved. If many applications reference the same dynamic link library, the saving in disk space can be significant.
- Since program modules only reference dynamic link libraries and do not contain the actual executable code, a dynamic link library can be updated without re-linking your application. When your application is executed, it will use the updated version of the dynamic link library.
- Dynamic link libraries also allow sharing of code and data between the applications that use them. If many applications that use the same dynamic link library are executing concurrently, the sharing of code and data segments improves memory utilization.

## 32.1 Creating Dynamic Link Libraries

Once you have developed the source for a library of functions, a number of steps are required to create a dynamic link library containing those functions.

First, you must compile your source using the "bd" compiler option. This option tells the compiler that the module you are compiling is part of a dynamic link library. Once you have successfully compiled your source, you must create a linker directive file that describes the attributes of your dynamic link library. The following lists the most common linker directives required to create a dynamic link library.

- The "SYSTEM" directive is used to specify that a dynamic link library is to be created.
- 2. The "EXPORT" directive is used to to specify which functions in the dynamic link library are to be exported.

#### Specifying exports in the source code

The "EXPORT" directive need not be used when the symbols to be exported are declared with the \_\_declspec( dllexport ) modifier in the source code. Such symbols are exported automatically, through special records inserted into the object files by the compiler.

#### Exporting C++ symbols and classes

Symbols exported via the "EXPORT" directive have to be entered in their mangled form. This makes it rather awkward to export C++ functions, classes or global objects. These symbols also often reference other compiler-generated symbols (invisible to the user) that need be exported together with the class/object. Using the \_\_declspec( dllexport ) method of exporting symbols is the preferred solution.

- The "OPTION" directive is used to specify attributes such as the name of the dynamic link library and how to allocate the automatic data segment when the dynamic link library is referenced.
- The "SEGMENT" directive is used to specify attributes of segments. For example, a segment may be read-only or read-write.

Once the dynamic link library is created, you must allow access to the dynamic link library to client applications that wish to use it. This can be done by creating an import library for the dynamic link library or creating a linker directive file that contains "IMPORT" directives for each of the entry points in the dynamic link library.

## 32.2 Creating a Sample Dynamic Link Library

Let us now create a dynamic link library using the following example.

```
#include <stdio.h>
#include <windows.h>
#if defined(__cplusplus)
#define EXPORTED extern "C" __declspec( dllexport )
#define EXPORTED __declspec( dllexport )
#endif
DWORD TlsIndex; /* Global Thread Local Storage index */
/* Error checking should be performed in following code */
BOOL APIENTRY LibMain ( HANDLE hinstDLL,
                       DWORD fdwReason,
                       LPVOID lpvReserved )
    switch( fdwReason ) {
    case DLL_PROCESS_ATTACH:
        /* do process initialization */
        /* create TLS index */
        TlsIndex = TlsAlloc();
        break;
    case DLL_THREAD_ATTACH:
        /* do thread initialization */
        /* allocate private storage for thread */
        ^{-} and save pointer to it ^{*}/
        TlsSetValue (TlsIndex, malloc(200));
```

```
case DLL_THREAD_DETACH:
        /* do thread cleanup */
        /* get the TLS value and free associated memory */
        free( TlsGetValue( TlsIndex ) );
    case DLL_PROCESS_DETACH:
        /* do process cleanup */
        /* free TLS index */
        TlsFree( TlsIndex );
        break;
                        /* indicate success */
    return(1);
    /* returning 0 indicates initialization failure */
EXPORTED void dll_entry_1( void )
    printf( "Hi from dll entry #1\n" );
EXPORTED void dll_entry_2( void )
    printf( "Hi from dll entry #2\n" );
```

#### Arguments:

hinstDLL

This is a handle for the DLL. It can be used as a argument to other functions such as GetModuleFileName.

fdwReason

This argument indicates why LibMain is being called. It can have one of the following values:

Value Meaning

**DLL PROCESS ATTACH** This value indicates that the DLL is attaching to the address space of the current process as a result of the process starting up or as a result of a call to LoadLibrary. A DLL can use this opportunity to initialize any instance data or to use the TlsAlloc function to allocate a Thread Local Storage (TLS) index.

> During initial process startup or after a call to LoadLibrary, the operating system scans the list of loaded DLLs for the process. For each DLL that has not already been called with the DLL\_PROCESS\_ATTACH value, the system calls the DLL's LibMain entry-point. This call is made in the context of the thread that caused the process address space to change, such as the primary thread of the process or the thread that called LoadLibrary.

**DLL\_THREAD\_ATTACH** This value indicates that the current process is creating a new thread. When this occurs, the system calls the LibMain entry-point of all DLLs currently attached to the process. The call is made in the context of the new thread. DLLs can use this opportunity to initialize a Thread Local Storage (TLS) slot for the thread. A thread calling the DLL's LibMain with the DLL\_PROCESS\_ATTACH value does not call LibMain with the DLL\_THREAD\_ATTACH value. Note that LibMain is called with this value only by threads created after the DLL is attached to the process.

When a DLL is attached by LoadLibrary, existing threads do not call the LibMain entry-point of the newly loaded DLL.

DLL\_THREAD\_DETACH This value indicates that a thread is exiting normally. If the DLL has stored a pointer to allocated memory in a TLS slot, it uses this opportunity to free the memory. The operating system calls the LibMain entry-point of all currently loaded DLLs with this value. The call is made in the context of the exiting thread. There are cases in which LibMain is called for a terminating thread even if the DLL never attached to the thread. For example, LibMain is never called with the DLL\_THREAD\_ATTACH value in the context of the thread in either of these two situations:

- The thread was the initial thread in the process, so the system called LibMain with the DLL\_PROCESS\_ATTACH value.
- The thread was already running when a call to the LoadLibrary function was made, so the system never called LibMain for it.

**DLL\_PROCESS\_DETACH** This value indicates that the DLL is detaching from the address space of the calling process as a result of either a normal termination or of a call to FreeLibrary. The DLL can use this opportunity to call the TlsFree function to free any TLS indices allocated by using TlsAlloc and to free any thread local data. When a DLL detaches from a process as a result of process termination or as a result of a call to FreeLibrary, the operating system does not call the DLL's LibMain with the DLL\_THREAD\_DETACH value for the individual threads of the process. The DLL is only given DLL\_PROCESS\_DETACH notification. DLLs can take this opportunity to clean up all resources for all threads attached and known to the DLL.

#### *lpvReserved*

This argument specifies further aspects of DLL initialization and cleanup. If fdwReason is DLL\_PROCESS\_ATTACH, lpvReserved is NULL for dynamic loads and non-NULL for static loads. If fdwReason is DLL\_PROCESS\_DETACH, lpvReserved is NULL if LibMain has been called by using FreeLibrary and non-NULL if LibMain has been called during process termination.

Return Value When the system calls the LibMain function with the DLL\_PROCESS\_ATTACH value, the function returns TRUE (1) if initialization succeeds or FALSE (0) if initialization fails.

> If the return value is FALSE (0) when LibMain is called because the process uses the LoadLibrary function, LoadLibrary returns NULL.

If the return value is FALSE (0) when LibMain is called during process initialization, the process terminates with an error. To get extended error information, call GetLastError.

When the system calls LibMain with any value other than DLL\_PROCESS\_ATTACH, the return value is ignored.

Assume the above example is contained in the file dllsamp.c. We can compile the file using the following command. Note that we must specify the "bd" compiler option.

C:\>wcc386 -bd dllsamp

Before we can link our example, we must create a linker directive file that describes the attributes and entry points of our dynamic link library. The following is a linker directive file, called dllsamp.lnk, that can be used to create the dynamic link library.

```
system nt_dll initinstance terminstance
export dll_entry_1_
export dll_entry_2_
file dllsamp
```

#### Notes:

- 1. The "SYSTEM" directive specifies that we are creating a Windows NT dynamic link library.
- When a dynamic link library uses the Open Watcom C/C++ run-time libraries, an automatic data segment is created each time a new process accesses the dynamic link library. For this reason, initialization code must be executed when a process accesses the dynamic link library for the first time. To achieve this, "INITINSTANCE" must be specified in the "SYSTEM" directive. Similarly, "TERMINSTANCE" must be specified so that the termination code is executed when a process has completed its access to the dynamic link library. If the Open Watcom C/C++ run-time libraries are not used, these options are not required.
- The "EXPORT" directive specifies the entry points into the dynamic link library. Note that the names specified in the "EXPORT" directive are appended with an underscore. This is the default naming convention used when compiling using the register-based calling convention. No underscore is required when compiling using the stack-based calling convention.

We can now create our dynamic link library by issuing the following command.

```
C: \>wlink @dllsamp
```

A file called dllsamp.dll will be created.

## 32.3 Using Dynamic Link Libraries

It is assumed that all symbols imported by a client application were declared with a \_\_\_declspec( dllimport ) modifier when the client application was compiled. At the link stage we have to tell the linker which dynamic libraries the client application should link to. Once we have created a dynamic link library, we must allow other applications to access the functions available in the dynamic link library. There are two ways to achieve this.

The first method is to create a linker directive file which contains an "IMPORT" directive for all entry points in the dynamic link library. The "IMPORT" directive provides the name of the entry point and the name of the dynamic link library. When creating an application that references a function in the dynamic link library, this linker directive file would be included as part of the linking process that created the application.

The second method is to use import libraries. An import library is a standard library that is created from a dynamic link library by using the Open Watcom Library Manager. It contains object modules that describe the entry points in a dynamic link library. The resulting import library can then be specified in a "LIBRARY" directive in the same way one would specify a standard library.

Using an import library is the preferred method of providing references to functions in dynamic link libraries. When a dynamic link library is modified, typically the import library corresponding to the modified dynamic link library is updated to reflect the changes. Hence, any directive file that specifies the import library in a "LIBRARY" directive need not be modified. However, if you are using "IMPORT" directives, you may have to modify the "IMPORT" directives to reflect the changes in the dynamic link library.

Let us create an import library for our sample dynamic link library we created in the previous section. We do this by issuing the following command.

```
C:\>wlib dllsamp +dllsamp.dll
```

A standard library called dllsamp.lib will be created.

Suppose the following sample program, contained in the file dlltest.c, calls the functions from our sample dynamic link library.

```
#include <stdio.h>
#include cess.h>
#if defined(__cplusplus)
#define IMPORTED extern "C" __declspec( dllimport )
#define IMPORTED __declspec( dllimport )
#endif
IMPORTED void dll_entry_1( void );
IMPORTED void dll_entry_2( void );
#define STACK_SIZE
                        8192
static void thread( void *arglist )
   printf( "Hi from thread\n" );
   _endthread();
int main( void )
{
   unsigned long tid;
   dll entry 1();
   tid = _beginthread( thread, STACK_SIZE, NULL );
   dll_entry_2();
   return(0);
```

We can compile and link our sample application by issuing the following command.

```
C:\>wc1386 -bm -l=nt dlltest dllsamp.lib
```

If we had created a linker directive file of "IMPORT" directives instead of an import library for the dynamic link library, the linker directive file, say dllimps.lnk, would be as follows.

```
import dll_entry_1_ dllsamp
import dll_entry_2_ dllsamp
```

Note that the names specified in the "IMPORT" directive are appended with an underscore. This is the default naming convention used when compiling using the register-based calling convention. No underscore is required when compiling using the stack-based calling convention.

To compile and link our sample application, we would issue the following command.

```
C:\>wcl386 -bm -l=nt dlltest -"@dllimps"
```

### 32.4 The Dynamic Link Library Data Area

The Open Watcom C/C++ 32-bit run-time library does not support the general case operation of DLLs in an execution environment where there is only one instance of the DATA segment (DGROUP) for that DLL.

There are two cases that can lead to a DLL executing with only one instance of the DGROUP.

- DLLs linked for 32-bit OS/2 without the MANYAUTODATA option.
- 2. DLLs linked for the Win32 API and executing under Win32s.

In these cases the run-time library startup code detects that there is only one instance of the DGROUP when a second process attempts to attach to the DLL. At that point, it issues a diagnostic for the user and then notifies the operating system that the second process cannot attach to the DLL.

Developers who require DLLs to operate when there is only one instance of the DGROUP can suppress the function which issues the diagnostic and notifies the operating system that the second process cannot attach to the DLL.

Doing so requires good behaviour on the part of processes attaching to the DLL. This good behaviour consists primarily of ensuring that the first process to attach to the DLL is also the last process to detach from the DLL thereby ensuring that the DATA segment is not released back to the free memory pool.

To suppress the function which issues the diagnostic and notifies the operating system that the second process cannot attach to the DLL, the developer must provide a replacement entry point with the following prototype:

```
int __disallow_single_dgroup( int );
```

This function should return zero to indicate that the detected single copy of the DATA segment is allowed.

## 33 Creating Windows NT POSIX Applications

This chapter describes how to compile and link POSIX applications for Windows NT. There are a number of issues to consider.

- Open Watcom does not provide its own POSIX libraries. You must use those included with the Microsoft Win32 SDK. They are libcpsx.lib, psxdll.lib and psxrtl.lib. If you installed the Win32 SDK component when you installed the Open Watcom software, you will find these libraries in the %WATCOM%\lib386\nt directory.
- Since you will be using Microsoft POSIX libraries compiled by the Microsoft compiler, you must follow the calling conventions used by Microsoft (i.e., the \_\_\_cdecl convention). The Open Watcom compiler can generate these calling conventions provided that the POSIX library routines are all properly prototyped.
- Open Watcom does not provide its own header files for use with the Microsoft POSIX libraries. The Microsoft Win32 SDK includes only a subset of the headers required for calling the POSIX library routines. If you installed the Win32 SDK component when you installed the Open Watcom software, you will find these headers in the %WATCOM%\sdk\posix\h and %WATCOM%\sdk\posix\h\sys directories. Take a look at these directories to see what is and what is not included.
- If you have the Microsoft compiler, then you will likely have access to the missing header files. If you do not have the Microsoft compiler, then you will have to define prototypes for any of the POSIX library routines that you use for which no prototypes are defined in any of the POSIX header files.
- There is one exception to the generation of the \_\_cdecl calling convention for appropriately prototyped functions. This is the main function. Since many Microsoft sample programs inappropriately declare the main function as \_\_\_cdecl, it was necessary to make a special case in the Open Watcom compilers to ignore the \_\_\_cdecl attribute when used for this entry point. To work around this problem, a special pragma is used. This is shown in the following example.
- Since we are going to use the Microsoft POSIX libraries rather than the Open Watcom libraries, we will use the "zl" compile option to instruct the Open Watcom compiler not to include references to Open Watcom libraries in the object files.

To illustrate the creation of a POSIX application, we will use a simple example. This program displays an identifying banner and then displays its arguments one at a time.

Example:

```
[POSIXSMP.C]
#include <unistd.h>
// The Win32 SDK doesn't provide a complete set of
// headers for the libraries (e.g., no stdio.h).
extern int __cdecl printf( char *, ... );
// Note: the "__cdecl" attribute is ignored for main().
int __cdecl main( int argc, char **argv )
    int i;
    printf( "POSIX sample program\n" );
    for(i = 0; i < argc; i++) {
        printf( "%d: %s\n", i, argv[i] );
    }
    return 0;
}
// Since the "__cdecl" attribute is ignored,
// make sure that parms go on the stack for main
// and that main gets the _ in the right place by
// using a pragma to do so.
#pragma aux main "_*" __parm [];
// The compiler emits references to these symbols,
// so make sure they get defined here to prevent
// unresolved references.
int _cstart_;
#pragma aux _cstart_ "*";
int __argc;
#pragma aux __argc "*";
```

The example program illustrates some of the special considerations required for using the Microsoft POSIX libraries rather than the Open Watcom libraries. There are also some special link time issues and these are addressed in the following sample "makefile".

#### Example:

```
[MAKEFILE]
posixsmp.exe : posixsmp.c posix.add makefile.
  set nt_include=
  \verb|set include=$(\watcom) \sdk\posix\h; $(\watcom) \sdk\posix\h\sys|
  wcc386 -bt=nt -oaxt -zl posixsmp.c
  wlink @posix.add file posixsmp sys nt_posix option map
posix.add:
  %create posix.add
  %append posix.add system begin nt_posix
  %append posix.add option osname='Windows NT character-mode posix'
%append posix.add libpath %WATCOM%\lib386\nt
  %append posix.add option nodefaultlib
  %append posix.add option start=___PosixProcessStartup
                       lib { libcpsx.lib psxrtl.lib psxdll.lib }
  %append posix.add
  %append posix.add format windows nt
  %append posix.add runtime posix
  %append posix.add end
```

A new "nt\_posix" system is defined in the posix.add file. This file is generated automatically by the makefile.

That is about all there is to creating a Windows NT POSIX application. One final note - make sure when using the Microsoft headers that all the library routines that you use are declared as \_\_\_cdecl otherwise your application will not run correctly.

# **OS/2 Programming Guide**

## 34 Creating 16-bit OS/2 1.x Applications

An OS/2 application can be one of the following; a fullscreen application, a PM-compatible application, or a Presentation Manager application. A fullscreen application runs in its own screen group. A PM-compatible application will run in an OS/2 fullscreen environment or in a window in the Presentation Manager screen group but does not take direct advantage of menus, mouse or other features available in the Presentation Manager. A Presentation Manager application has full access to the complete set of user-interface tools such as menus, icons, scroll bars, etc.

This chapter deals with the creation of OS/2 fullscreen applications. For information on creating Presentation Manager applications, refer to the section entitled "Programming for OS/2 Presentation Manager" on page 257.

We will illustrate the steps to creating 16-bit OS/2 1.x applications by taking a small sample application and showing you how to compile, link, run and debug it.

## 34.1 The Sample Application

To demonstrate the creation of 16-bit OS/2 1.x applications using command-line oriented tools, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
    printf( "Hello world\n" );
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
    cout << "Hello world" << endl;</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

## 34.2 Building and Running the Sample OS/2 1.x Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
[C:\]wcl -l=os2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
[C:\]wcl -l=os2 hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc hello.c
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 155, 0 warnings, 0 errors
Code size: 17
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating an OS/2 16-bit executable
```

Provided that no errors were encountered during the compile or link phases, the "hello" program may now be run.

```
[C:\]hello
Hello world
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). It is hello.exe that is run by OS/2 when you enter the "hello" command.

## 34.3 Debugging the Sample OS/2 1.x Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL command, this is fairly straightforward. WCL recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
[C:\]wcl -l=os2 -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
[C:\]wcl -l=os2 -d2 hello.c
Open Watcom C/C++16 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
       wcc hello.c -d2
Open Watcom C16 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 155, 0 warnings, 0 errors
Code size: 23
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating an OS/2 16-bit executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

For OS/2, you should also include the BINP\DLL directory in the "LIBPATH" directive of the system configuration file CONFIG.SYS. It contains the Open Watcom Debugger Dynamic Link Libraries (DLLs).

```
Example:
```

```
libpath=c:\watcom\binp\dll
```

To request the Open Watcom Debugger to assist in debugging the application, the following command may be issued.

```
[C:\]wd hello
```

It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled Open Watcom Debugger User's Guide.

# 35 Creating 32-bit OS/2 Applications

An OS/2 application can be one of the following; a fullscreen application, a PM-compatible application, or a Presentation Manager application. A fullscreen application runs in its own screen group. A PM-compatible application will run in an OS/2 fullscreen environment or in a window in the Presentation Manager screen group but does not take direct advantage of menus, mouse or other features available in the Presentation Manager. A Presentation Manager application has full access to the complete set of user-interface tools such as menus, icons, scroll bars, etc.

This chapter deals with the creation of OS/2 fullscreen applications. For information on creating Presentation Manager applications, refer to the section entitled "Programming for OS/2 Presentation Manager" on page 257.

We will illustrate the steps to creating 32-bit OS/2 applications by taking a small sample application and showing you how to compile, link, run and debug it.

# 35.1 The Sample Application

To demonstrate the creation of 32-bit OS/2 applications using command-line oriented tools, we introduce a simple sample program. For our example, we are going to use the famous "hello" program.

```
#include <stdio.h>
void main()
    printf( "Hello world\n" );
```

The C++ version of this program follows:

```
#include <iostream.h>
void main()
    cout << "Hello world" << endl;</pre>
```

The goal of this program is to display the message "Hello world" on the screen. The C version uses the C library printf routine to accomplish this task. The C++ version uses the "iostream" library to accomplish this task. We will take you through the steps necessary to produce this result.

## 35.2 Building and Running the Sample OS/2 Application

To compile and link our example program which is stored in the file hello.c, enter the following command:

```
[C:\]wcl386 -l=os2v2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
[C:\]wcl386 -1=os2v2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 24
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating an OS/2 32-bit executable
```

Provided that no errors were encountered during the compile or link phases, the "hello" program may now be run.

```
[C:\]hello
Hello world
```

If you examine the current directory, you will find that two files have been created. These are hello.obj (the result of compiling hello.c) and hello.exe (the result of linking hello.obj with the appropriate Open Watcom C/C++ libraries). It is hello.exe that is run by OS/2 when you enter the "hello" command.

# 35.3 Debugging the Sample OS/2 Application

Let us assume that you wish to debug your application in order to locate an error in programming. In the previous section, the "hello" program was compiled with default compile and link options. When debugging an application, it is useful to refer to the symbolic names of routines and variables. It is also convenient to debug at the source line level rather than the machine language level. To do this, we must direct both the compiler and linker to include additional debugging information in the object and executable files. Using the WCL386 command, this is fairly straightforward. WCL386 recognizes the Open Watcom C/C++ compiler "debug" options and will create the appropriate debug directives for the Open Watcom Linker.

For example, to compile and link the "hello" program with debugging information, the following command may be issued.

```
[C:\]wcl386 -l=os2v2 -d2 hello.c
```

The typical messages that appear on the screen are shown in the following illustration.

```
[C:\]wc1386 -l=os2v2 -d2 hello.c
Open Watcom C/C++32 Compile and Link Utility
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1988-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
        wcc386 hello.c -d2
Open Watcom C32 Optimizing Compiler
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1984-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
hello.c: 6 lines, included 174, 0 warnings, 0 errors
Code size: 45
Open Watcom Linker
Copyright (c) 2002-2021 the Open Watcom Contributors. All Rights Reserved.
Portions Copyright (c) 1985-2002 Sybase, Inc. All Rights Reserved.
Source code is available under the Sybase Open Watcom Public License.
See http://www.openwatcom.org/ for details.
loading object files
searching libraries
creating an OS/2 32-bit executable
```

The "d2" option requests the maximum amount of debugging information that can be provided by the Open Watcom C/C++ compiler. WCL386 will make sure that this debugging information is included in the executable file that is produced by the linker.

The "Code size" value is larger than in the previous example since selection of the "d2" option results in fewer code optimizations by default. You can request more optimization by specifying the appropriate options. However, you do so at the risk of making it more difficult for yourself to determine the relationship between the object code and the original source language code.

To request the Open Watcom Debugger to assist in debugging the application, the following command may be issued.

```
[C:\]wd hello
```

It would be too ambitious to describe the debugger in this introductory chapter so we refer you to the book entitled Open Watcom Debugger User's Guide.

# **36** OS/2 2.x Multi-threaded Applications

This chapter describes how to create multi-threaded applications. A multi-threaded application is one whose tasks are divided among several threads of execution. A process is an executing application and the resources it uses. A thread is the smallest unit of execution within a process. Each thread has its own stack and a set of machine registers and shares all resources with its parent process. The path of execution of one thread does not affect that of another; each thread is an independent entity.

Typically, an application has a single thread of execution. In this type of application, all tasks, once initiated, are completed before the next task begins. In contrast, tasks in a multi-threaded application can be performed concurrently since more than one thread is executing at once. For example, each thread may be designed to perform a separate task.

# 36.1 Programming Considerations

Since a multi-threaded application consists of many threads of execution, there are a number of issues that you must consider.

Since threads share the resources of its parent, it may be necessary to serialize access to these resources. For example, if your application has a function that displays information on the console and is used by all threads, it is necessary to allow only one thread to use that function at any time. That is, once a thread calls that function, the function should ensure that no other thread displays information until all information for the initial thread has been displayed. An example of such a function is the printf library function.

Another issue that must be considered when creating multi-threaded applications is global variables. If you have global variables that contain thread-specific information, there must be an instance of each global variable for each thread. An example of such a variable is the errno global variable defined in the run-time libraries. If an error condition was created by a thread, you would not want it to affect the execution of other threads. Therefore, each thread should contain its own instance of this variable.

# 36.2 Creating Threads

Each application initially contains a single thread. The run-time libraries contain two functions that create and terminate threads of execution. The function \_beginthread creates a thread of execution and the function \_endthread ends a thread of execution. The macro \_threadid can be used to determine the current thread identifier.

**WARNING!** If any thread calls a library function, you must use the \_beginthread function to create the thread. Do not use the DosCreateThread API function.

#### 36.2.1 Creating a New Thread

The \_beginthread function creates a new thread. It is defined as follows.

where description

start\_address is the address of the function that will be called when the newly created thread is executed.

When the thread returns from that function, the thread will be terminated. Note that a call

to the \_endthread function will also terminate the thread.

**stack\_bottom** specifies the bottom of the stack to be used by the thread. Note that this argument is

ignored as it is only needed to simplify the port of OS/2 1.x multi-threaded applications to OS/2 2.x. Under OS/2 2.x, the operating system allocates the stack for the new thread. A

value of NULL may be specified.

**stack\_size** specifies the size of the stack to be allocated by the operating system for the new thread.

The stack size should be a multiple of 4K.

arglist is passed as an argument to the function specified by start\_address. If no argument is

required, a value of NULL can be specified.

If a new thread is successfully created, the thread identifier of the new thread is returned. Otherwise, a value of -1 is returned.

The header file process.h contains the definition of the \_beginthread function.

#### 36.2.2 Terminating the Current Thread

The \_endthread function terminates the current thread. It is defined as follows.

```
void _endthread( void )
```

The header file process.h contains the definition of the \_endthread function.

### 36.2.3 Getting the Current Thread Identifier

The \_threadid macro can be used to determine the current thread identifier. It is defined as follows.

```
int *__threadid(void);
#define _threadid())
```

The header file stddef.h contains the definition of the \_threadid macro.

## 36.3 A Multi-threaded Example

Let us create a simple multi-threaded application. The source code for this example can be found in \watcom\samples\os2.

```
#include cess.h>
#include <stdio.h>
#include <stddef.h>
#define INCL_DOS
#include <os2.h>
static volatile int
                       NumThreads:
static volatile int
                       HoldThreads;
#define NUM THREADS
#define STACK_SIZE
                        32768
static void a_thread( void *arglist )
{
    while( HoldThreads ) {
       DosSleep(1);
   printf( "Hi from thread %d\n", *_threadid );
   DosEnterCritSec();
    --NumThreads;
   DosExitCritSec();
   _endthread();
int main ( void )
/*******
{
   printf( "Initial thread id = %d\n", *_threadid );
   NumThreads = 0:
   HoldThreads = 1;
    /* initial thread counts as 1 */
    for( i = 2; i <= NUM_THREADS; ++i ) {</pre>
       if( _beginthread( a_thread, NULL, STACK_SIZE, NULL ) == -1 ) {
           printf( "creation of thread %d failed\n", i );
        } else {
           ++NumThreads;
    HoldThreads = 0;
    while( NumThreads != 0 ) {
       DosSleep(1);
   return(0);
```

Note:

In the function a\_thread, DosEnterCritSec and DosExitCritSec are called when we modify the variable NumThreads. This ensures that the action of extracting the value of NumThreads from memory, incrementing the value, and storing the new result into memory, occurs without interruption. If these functions were not called, it would be possible for two threads to extract the value of NumThreads from memory before an update occurred.

Let us assume that the file mthread.c contains the above example. Before compiling the file, make sure that the WATCOM environment variable is set to the directory in which you installed Open Watcom C/C++. Also, the INCLUDE environment variable must include the \watcom\h\os2 and \watcom\h directories ("WATCOM" is the directory in which Open Watcom C/C++ was installed).

We can now compile and link the application by issuing the following command.

```
[C:\]wcl386 -bt=os2 -bm -l=os2v2 mthread
```

The "bm" option must be specified since we are creating a multi-threaded application. If your multi-threaded application contains more than one module, each module must be compiled using the "bm" switch.

The "I" option specifies the target system for which the application is to be linked. The system name os2v2 is defined in the file wlsystem.lnk which is located in the "BINW" subdirectory of the directory in which you installed Open Watcom C/C++.

The multi-threaded application is now ready to be run.

#### 36.4 Thread Limits

There is a limit to the number of threads an application can create under 16-bit OS/2. The default limit is 32. This limit can be adjusted by statically initializing the unsigned global variable \_\_\_MaxThreads.

Under 32-bit OS/2, there is no limit to the number of threads an application can create. However, due to the way in which multiple threads are supported in the Open Watcom libraries, there is a small performance penalty once the number of threads exceeds the default limit of 32 (this number includes the initial thread). If you are creating more than 32 threads and wish to avoid this performance penalty, you can redefine the threshold value of 32. You can statically initialize the global variable \_\_\_MaxThreads.

By adding the following line to your multi-threaded application, the new threshold value will be set to 48.

```
unsigned __MaxThreads = { 48 };
```

# 37 OS/2 2.x Dynamic Link Libraries

A dynamic link library, like a standard library, is a library of functions. When an application uses functions from a standard library, the library functions referenced by the application become part of the executable module. This form of linking is called static linking. When an application uses functions from a dynamic link library, the library functions referenced by the application are not included in the executable module. Instead, the executable module contains references to these functions which are resolved when the application is loaded. This form of linking is called dynamic linking.

Let us consider some of the advantages of using dynamic link libraries over standard libraries.

- Functions in dynamic link libraries are not linked into your program. Only references to the functions in dynamic link libraries are placed in the program module. These references are called import definitions. As a result, the linking time is reduced and disk space is saved. If many applications reference the same dynamic link library, the saving in disk space can be significant.
- Since program modules only reference dynamic link libraries and do not contain the actual executable code, a dynamic link library can be updated without re-linking your application. When your application is executed, it will use the updated version of the dynamic link library.
- Dynamic link libraries also allow sharing of code and data between the applications that use them. If many applications that use the same dynamic link library are executing concurrently, the sharing of code and data segments improves memory utilization.

# 37.1 Creating Dynamic Link Libraries

Once you have developed the source for a library of functions, a number of steps are required to create a dynamic link library containing those functions.

First, you must compile your source using the "bd" compiler option. This option tells the compiler that the module you are compiling is part of a dynamic link library. Once you have successfully compiled your source, you must create a linker directive file that describes the attributes of your dynamic link library. The following lists the most common linker directives required to create a dynamic link library.

- The "SYSTEM" directive is used to specify that a dynamic link library is to be created.
- 2. The "EXPORT" directive is used to to specify which functions in the dynamic link library are to be exported.

#### Specifying exports in the source code

The "EXPORT" directive need not be used when the symbols to be exported are declared with the \_\_export type qualifier in the source code. Such symbols are exported automatically, through special records inserted into the object files by the compiler.

- The "OPTION" directive is used to specify attributes such as the name of the dynamic link library and how to allocate the automatic data segment when the dynamic link library is
- The "SEGMENT" directive is used to specify attributes of segments. For example, a segment may be read-only or read-write.

Once the dynamic link library is created, you must allow access to the dynamic link library to client applications that wish to use it. This can be done by creating an import library for the dynamic link library or creating a linker directive file that contains "IMPORT" directives for each of the entry points in the dynamic link library.

# 37.2 Creating a Sample Dynamic Link Library

Let us now create a dynamic link library using the following example.

```
#include <stdio.h>
#include <os2.h>
#if defined(__cplusplus)
#define EXTERNC extern "C"
#else
#define EXTERNC
#endif
unsigned APIENTRY LibMain( unsigned hmod, unsigned termination )
    if( termination ) {
       /* DLL is detaching from process */
    } else {
       /* DLL is attaching to process */
    return(1);
}
EXTERNC void dll_entry_1( void )
    printf( "Hi from dll entry #1\n" );
EXTERNC void dll_entry_2( void )
   printf( "Hi from dll entry #2\n" );
```

32-bit OS/2 DLLs can include a LibMain entry point when you are using the Open Watcom C/C++ run-time libraries.

#### Arguments:

hmod

This is a handle for the DLL.

termination

A 0 value indicates that the DLL is attaching to the address space of the current process as a result of the process starting up or as a result of a call to DosLoadModule. A DLL can use this opportunity to initialize any instance data.

A non-zero value indicates that the DLL is detaching from the address space of the calling process as a result of either a normal termination or of a call to DosFreeModule.

**Return Value** The LibMain function returns 1 if initialization succeeds or 0 if initialization fails.

If the return value is 0 when LibMain is called because the process uses the DosLoadModule function, DosLoadModule returns an error.

If the return value is 0 when LibMain is called during process initialization, the process terminates with an error.

Assume the above example is contained in the file dllsamp.c. We can compile the file using the following command. Note that we must specify the "bd" compiler option.

```
[C:\]wcc386 -bd dllsamp
```

Before we can link our example, we must create a linker directive file that describes the attributes and entry points of our dynamic link library. The following is a linker directive file, called dllsamp.lnk, that can be used to create the dynamic link library.

```
system os2v2 dll initinstance terminstance
option manyautodata
export dll entry 1
export dll_entry_2_
file dllsamp
```

#### Notes:

- 1. The "SYSTEM" directive specifies that we are creating a 32-bit OS/2 dynamic link library.
- The "MANYAUTODATA" option specifies that the automatic data segment is allocated for every instance of the dynamic link library. This option must be specified only for a dynamic link library that uses the Open Watcom C/C++ run-time libraries. If the Open Watcom C/C++ run-time libraries are not used, this option is not required. Our example does use the Open Watcom C/C++ run-time libraries so we must specify the "MANYAUTODATA" option.

As was just mentioned, when a dynamic link library uses the Open Watcom C/C++ run-time libraries, an automatic data segment is created each time a process accesses the dynamic link library. For this reason, initialization code must be executed when a process accesses the dynamic link library for the first time. To achieve this, "INITINSTANCE" must be specified in the "SYSTEM" directive. Similarly, "TERMINSTANCE" must be specified so that the termination code is executed when a process has completed its access to the dynamic link library. If the Open Watcom C/C++ run-time libraries are not used, these options are not required.

The "EXPORT" directive specifies the entry points into the dynamic link library. Note that the names specified in the "EXPORT" directive are appended with an underscore. This is the default naming convention used when compiling using the register-based calling convention. No underscore is required when compiling using the stack-based calling convention.

We can now create our dynamic link library by issuing the following command.

```
[C:\]wlink @dllsamp
```

A file called dllsamp.dll will be created.

## 37.3 Using Dynamic Link Libraries

Once we have created a dynamic link library, we must allow other applications to access the functions available in the dynamic link library. There are two ways to achieve this.

The first method is to create a linker directive file which contains an "IMPORT" directive for all entry points in the dynamic link library. The "IMPORT" directive provides the name of the entry point and the name of the dynamic link library. When creating an application that references a function in the dynamic link library, this linker directive file would be included as part of the linking process that created the application.

The second method is to use import libraries. An import library is a standard library that is created from a dynamic link library by using the Open Watcom Library Manager. It contains object modules that describe the entry points in a dynamic link library. The resulting import library can then be specified in a "LIBRARY" directive in the same way one would specify a standard library.

Using an import library is the preferred method of providing references to functions in dynamic link libraries. When a dynamic link library is modified, typically the import library corresponding to the modified dynamic link library is updated to reflect the changes. Hence, any directive file that specifies the import library in a "LIBRARY" directive need not be modified. However, if you are using "IMPORT" directives, you may have to modify the "IMPORT" directives to reflect the changes in the dynamic link library.

Let us create an import library for our sample dynamic link library we created in the previous section. We do this by issuing the following command.

```
[C:\]wlib dllsamp +dllsamp.dll
```

A standard library called dllsamp.lib will be created.

Suppose the following sample program, contained in the file dlltest.c, calls the functions from our sample dynamic link library.

```
#include <stdio.h>
#if defined(__cplusplus)
#define EXTERNC extern "C"
#else
#define EXTERNC
#endif
EXTERNC void dll_entry_1( void );
EXTERNC void dll_entry_2( void );
int main ( void )
    dll_entry_1();
    dll_entry_2();
    return(0);
```

We can compile and link our sample application by issuing the following command.

```
[C:\]wcl386 -l=os2v2 dlltest dllsamp.lib
```

If we had created a linker directive file of "IMPORT" directives instead of an import library for the dynamic link library, the linker directive file, say dllimps.lnk, would be as follows.

```
import dll_entry_1_ dllsamp
import dll_entry_2_ dllsamp
```

Note that the names specified in the "IMPORT" directive are appended with an underscore. This is the default naming convention used when compiling using the register-based calling convention. No underscore is required when compiling using the stack-based calling convention.

To compile and link our sample application, we would issue the following command.

```
[C:\]wcl386 -l=os2v2 dlltest -"@dllimps"
```

## 37.4 The Dynamic Link Library Data Area

The Open Watcom C/C++ 32-bit run-time library does not support the general case operation of DLLs in an execution environment where there is only one instance of the DATA segment (DGROUP) for that DLL.

There are two cases that can lead to a DLL executing with only one instance of the DGROUP.

- DLLs linked for 32-bit OS/2 without the MANYAUTODATA option.
- 2. DLLs linked for the Win32 API and executing under Win32s.

In these cases the run-time library startup code detects that there is only one instance of the DGROUP when a second process attempts to attach to the DLL. At that point, it issues a diagnostic for the user and then notifies the operating system that the second process cannot attach to the DLL.

Developers who require DLLs to operate when there is only one instance of the DGROUP can suppress the function which issues the diagnostic and notifies the operating system that the second process cannot attach to the DLL.

Doing so requires good behaviour on the part of processes attaching to the DLL. This good behaviour consists primarily of ensuring that the first process to attach to the DLL is also the last process to detach from the DLL thereby ensuring that the DATA segment is not released back to the free memory pool.

To suppress the function which issues the diagnostic and notifies the operating system that the second process cannot attach to the DLL, the developer must provide a replacement entry point with the following prototype:

```
int __disallow_single_dgroup( int );
```

This function should return zero to indicate that the detected single copy of the DATA segment is allowed.

# 37.5 Dynamic Link Library Initialization/Termination

Each dynamic link library (DLL) has an initialization and termination routine associated with it. The initialization routine can either be called the first time any process accesses the DLL ("INITGLOBAL" is specified at link time) or each time a process accesses the DLL ("INITINSTANCE" is specified at link time). Similarly, the termination routine can either be called when all processes have completed their access of the DLL ("TERMGLOBAL" is specified at link time) or each time a process completes its access of the DLL ("TERMINSTANCE" is specified at link time).

For a DLL that uses the C/C++ run-time libraries, initialization and termination of the C/C++ run-time environment is performed automatically. It is also possible for a DLL to do its own special initialization and termination process.

The C/C++ run-time environment provides two methods for calling user-written DLL initialization and termination code.

- 1. If you provide your own version of LibMain then it will be called for initialization and termination. The use of LibMain is described earlier in this chapter.
- 2. If you do not provide your own version of LibMain then a default version is linked in from the library. This version will call \_\_dll\_initialize for DLL initialization and \_\_dll\_terminate for DLL termination. Default stub versions of these two routines are included in the run-time library. If you wish to perform additional initialization/termination that is specific to your dynamic link library, you may write your own versions of these routines.

Once the C/C++ run-time environment is initialized, the routine \_\_dll\_initialize is called. After the C/C++ run-time environment is terminated, the routine \_\_dll\_terminate is called. This last point is important since it means that you cannot do any run-time calls in the termination routine.

The initialization and termination routines return an integer. A value of 0 indicates failure; a value of 1 indicates success. The following example illustrates sample initialization/termination routines.

```
#include <stdlib.h>
#define WORKING_SIZE (64 * 1024)
char *WorkingStorage;
#if defined(__cplusplus)
#define EXTERNC extern "C"
#define EXTERNC
#endif
void __dll_finalize( void );
EXTERNC int __dll_initialize( void )
    WorkingStorage = malloc( WORKING_SIZE );
    if( WorkingStorage == NULL ) return( 0 );
    atexit( __dll_finalize );
    return(1);
void __dll_finalize( void )
    free ( WorkingStorage );
EXTERNC int __dll_terminate( void )
    return(1);
EXTERNC void dll_entry( void )
    /* use array WorkingStorage */
```

In the above example, the process initialization routine allocates storage that the dynamic link library needs, the routine dll\_entry uses the storage, and the process termination routine frees the storage allocated in the initialization routine.

# 38 Programming for OS/2 Presentation Manager

Basically, there are two classes of C/C++ applications that can run in a windowed environment.

The first are those C/C++ applications that do not use any of the Presentation Manager API functions; they are strictly C/C++ applications that do not rely on the features of a particular operating system.

The second class of C/C++ applications are those that actually call Presentation Manager API functions directly. These are applications that have been tailored for the Presentation Manager operating environment.

It is assumed that the reader is familiar with the concepts of Presentation Manager programming.

# 38.1 Porting Existing C/C++ Applications

Suppose you have a set of C/C++ applications that previously ran under DOS and you now wish to run them under OS/2. To achieve this, simply recompile your application and link with the appropriate libraries. Depending on the method with which you linked your application, it can run in an OS/2 fullscreen environment, a PM-compatible window, or as a Presentation Manager application. An OS/2 fullscreen application runs in its own screen group. A PM-compatible application will run in an OS/2 fullscreen environment or in a window in the Presentation Manager screen group but does not take direct advantage of menus, mouse or other features available in the Presentation Manager. A Presentation Manager application has full access to the complete set of user-interface tools such as menus, icons, scroll bars, etc. However, porting a console oriented application to Presentation Manager often requires significant effort and a substantial redesign of the application.

#### 38.1.1 An Example

Very little effort is required to port an existing C/C++ application to OS/2. Let us try to run the following sample program (contained in the file hello.c).

```
#include <stdio.h>
int main ( void )
    printf( "Hello world!\n" );
    return(0);
```

An equivalent C++ program follows:

```
#include <iostream.h>
int main( void )
    cout << "Hello world" << endl;</pre>
    return(0);
}
```

First we must compile the file hello.c by issuing the following command.

```
[C:\]wcc386 hello
```

Once we have successfully compiled the file, we can link it by issuing the following command.

```
[C:\]wlink sys os2v2 file hello
```

It is also possible to compile and link in one step, by issuing the following command.

```
[C:\] wcl386 -l=os2v2 hello
```

This will create a PM-compatible application. If you wish to create a fullscreen application, link with the following command.

```
[C:\]wlink sys os2v2 fullscreen file hello
```

# 38.2 Calling Presentation Manager API Functions

It is also possible for a C/C++ application to create its own windowing environment. This is achieved by calling PM API functions directly from your C/C++ program. The techniques for developing these applications can be found in the *OS/2 Technical Library*.

A number of C/C++ include files (files with extension .h) are provided which define Presentation Manager data structures and constants. They are located in the \watcom\h\os2 directory. These include files are roughly equivalent to the C/C++ header files that are available with the IBM OS/2 Developer's Toolkit.

A sample C/C++ Presentation Manager application is also located in the \watcom\samples\os2 directory. It is contained in the files shapes.c (C variant) and shapes.cpp (C++ variant, nearly identical). The file shapes.c contains the following.

```
#include <stdlib.h>
#define INCL_WIN
#define INCL_GPI
#include <os2.h>
int
                SizeX;
int
               SizeY:
HWND
               FrameHandle;
               hMessageQueue;
               AnchorBlock;
HAR
```

```
static int
                Random( int high )
    return( ( (double) rand() / 32767 ) * high );
static void NewColor( HPS ps )
    GpiSetColor(ps, Random(15) + 1);
^{\prime\prime} Draw a rectangular shape of random size and color at random position ^{\star\prime}
static void DrawEllipse(HWND hwndWindow)
    POINTL
               ptl;
    HPS
               ps;
    static int Odd = 0;
               parm1,parm2;
    ps = WinGetPS( hwndWindow );
    ptl.x = Random( SizeX );
    ptl.y = Random( SizeY );
    GpiMove( ps, &ptl );
    ptl.x = Random(SizeX);
    ptl.y = Random( SizeY );
    parm1 = Random(50);
    parm2 = Random(50);
    if( Random( 10 ) >= 5 ) {
        NewColor( ps );
        GpiBox( ps, DRO_FILL, &ptl, 0, 0 );
        NewColor( ps );
        GpiBox( ps, DRO_OUTLINE, &ptl, 0, 0 );
    } else {
        NewColor( ps );
        GpiBox( ps, DRO_FILL, &ptl, parm1, parm2 );
        NewColor( ps );
        GpiBox( ps, DRO_OUTLINE, &ptl, parm1, parm2 );
    Odd &= 1;
    WinReleasePS( ps );
/* Client window procedure */
MRESULT EXPENTRY MainDriver( HWND hwnd, USHORT msg, MPARAM mp1, MPARAM mp2 )
    HPS
                ps;
    RECTL
                rcl;
    switch( msg ) {
    case WM_CREATE:
        /* Start a 150ms timer on window creation */
        WinStartTimer( AnchorBlock, hwnd, 1, 150 );
        break;
    case WM_TIMER:
        /* Draw another ellipse on each timer tick */
        DrawEllipse( hwnd );
        return(0);
    case WM_SIZE:
        /* Remember new dimensions when window is resized */
        SizeX = SHORT1FROMMP( mp2 );
        SizeY = SHORT2FROMMP(mp2);
        return(0);
    case WM_PAINT:
        /* Handle paint events */
        ps = WinBeginPaint( hwnd, NULL, NULL );
        WinQueryWindowRect( hwnd, &rcl );
        WinFillRect(ps, &rcl, CLR_WHITE);
        WinEndPaint( ps );
        return(0);
```

```
^{\prime} Let the default window procedure handle all other messages ^{*\prime}
    return( WinDefWindowProc( hwnd, msg, mp1, mp2 ) );
int
       main()
{
   ULONG
                style;
    QMSG
                amsa;
   HWND
               WinHandle;
    /* Initialize windowing and create message queue */
    AnchorBlock = WinInitialize( 0 );
    if( AnchorBlock == 0 ) return( 0 );
   hMessageQueue = WinCreateMsgQueue( AnchorBlock, 0 );
    if( hMessageQueue == 0 ) return( 0 );
    /* Register window class */
    if( !WinRegisterClass( AnchorBlock, "Watcom", (PFNWP)MainDriver,
                           CS_SIZEREDRAW, 0 ) ) {
        return(0);
    /* Create frame and client windows */
    style = FCF_TITLEBAR | FCF_SYSMENU | FCF_SIZEBORDER | FCF_MINMAX |
           FCF_SHELLPOSITION | FCF_TASKLIST;
    FrameHandle = WinCreateStdWindow( HWND_DESKTOP, WS_VISIBLE, &style,
                                       "Watcom",
                                       "Shapes - C sample",
                                       0, NULL, 0, &WinHandle);
    /* If window creation failed, exit immediately! */
    if(FrameHandle == 0) return(0);
    /* Message loop */
    while(WinGetMsg(AnchorBlock, &qmsg, NULL, 0, 0)) {
        WinDispatchMsg( AnchorBlock, &qmsg );
    /* Shut down and clean up */
   WinDestroyWindow(FrameHandle);
    WinDestroyMsgQueue( hMessageQueue );
   WinTerminate ( AnchorBlock );
    return(1);
}
```

You can compile, link and run this demonstration by issuing the following commands.

```
[C:\]wcl386 -l=os2v2_pm shapes
[C:\]shapes
```

# 39 Developing an OS/2 Physical Device Driver

In this chapter, we discuss the development of Physical Device Drivers (PDD) for OS/2. The tools used in the creation of the sample PDD are:

- the 16-bit Open Watcom C compiler
- the Open Watcom Assembler
- the Open Watcom Make utility

The sample Physical Device Driver that we are going to build, HRTIMER.SYS, provides access to a high resolution timer. Additional sources of information on PDDs can be found in the following:

- OS/2 2.0 Technical Library Physical Device Driver Reference
- Writing OS/2 2.1 Device Drivers in C by Steve J. Mastrianni
- An OS/2 High Resolution Software Timer by Derek Williams, an article which appeared in the Fall 1991 issue of *IBM Personal Systems Developer* magazine. The source code for this device driver was adapted from the magazine article. For detailed information on the way this device driver works, please read that article.

HRTIMER. SYS is a 16-bit device driver which runs under OS/2 1.x and 2.x/3.x. It has a resolution of 840 nanoseconds (i.e., 1 tick of the Intel 8253/8254 timer = 840 nanoseconds).

Here are some notes on creating Physical Device Drivers using Open Watcom software tools.

- A Physical Device Driver is linked as a DLL.
- The first segment must be a data segment, the next a code segment.
- By default only the first two segments remain after initialization, extra segments have to be marked IOPL.
- The assembler file, DEVSEGS.ASM, defines the segment ordering.
- #pragma dataseg and #pragma codeseg are used to get various pieces of code and data into the correct segments.
- The \_HEADER segment contains the device header and must be at the beginning of the data segment.
- The \_INITCODE and \_INITDATA segments are used to place initialization code and data at the end so it can be discarded by OS/2.

To compile the source code for the 16-bit Physical Device Drivers, we use the following options:

#### OS/2 Programming Guide

-zl

-bt=os2 build target is OS/2 -ms 16-bit small code/small data model -5 Pentium optimizations (this is optional) inline math and intrinsic functions (this is optional) -omi no stack checking -.5 DS is pegged to DGROUP -zdp FS floats, i.e. not fixed to a segment -zff GS floats, i.e. not fixed to a segment SS != DGROUP -z.u

remove default library information

To link the object code for the 16-bit Physical Device Drivers, we use the following options:

name hrtimer.sys to name the executable file.

sys os 2 dll initglobal to link a 16-bit OS/2 DLL. Specifying INITGLOBAL will cause the

initialization routine to be called the first time the dynamic link library is loaded.

*option map* to generate a map file.

*option quiet* to minimize the number of linker informational messages.

*lib os2* to include the 16-bit OS2. LIB library file.

file ... to include the component object files of the device driver.

The sample files used to create the Physical Device Driver and the programs that use it are located in the \WATCOM\SRC\OS2\PDD directory. The Physical Device Driver files are:

**DEVSEGS.ASM** This small assembler file orders the segment definitions in the executable file.

\_DAT. \_BSS

\_INITDATA (discardable)

Code Segments \_TEXT

\_INITCODE (discardable)

**HEADER.C** The first thing that must follow the EXE Header is the Device Driver Header.

*STRATEGY.C* This is the resident portion of the Strategy routine.

STRATINI.C This is the discardable portion of the Strategy routine, the initialization code and

data.

#### Developing an OS/2 Physical Device Driver

HRTIMER.H This file contains the definition of the timer "timestamp" structure.

HRDEV.H This file contains definitions for the Intel 8253 hardware timer.

DEVHDR.H This file contains definitions for the Device Driver Header structure (see page

3-2, "Physical Device Driver Header" of PDD Reference).

DEVDEFS.H This file provides type definitions.

DEVREQP.H This file contains definitions for the Device Driver Request Packets.

DEVAUX.H This file contains definitions for the Device Driver Help (DevHlp) routines.

The demonstration program files are:

HRTEST.C This file is a sample C program that shows how to use the device driver to calculate elapsed

> times. It demonstrates how to open the device driver, read timestamps from it and close it. It factors in the overhead of the read and has a function that is used to calculate elapsed

time from a start and stop timestamp.

TIMER.C This file is a sample C program that can be used to time other applications. It also uses the

device driver.

To build the device driver and demonstration programs, set your current directory to \WATCOM\SRC\OS2\PDD and type:

wmake

To install the device driver, put the following statement in your CONFIG. SYS file.

```
DEVICE=\WATCOM\SRC\OS2\PDD\HRTIMER.SYS
```

You must then reboot OS/2.

To run the test program, use the following command-line:

```
HRTEST [milliseconds]
```

For [milliseconds], you can enter any number (e.g., 2000 which is 2 seconds).

HRTEST. EXE will issue a DosSleep for the amount of milliseconds specified or will use a default if no command-line parameter is given. It will get a timestamp from the device driver before and after the DosSleep and will calculate the elapsed time of that sleep and display the results. It will do this continuously until Ctrl/C or Ctrl/Break is pressed.

Keep in mind that DosSleep has a granularity of 32 milliseconds. Any discrepancy between the number of milliseconds used for the DosSleep and the elapsed time results from the timer are the fault of this granularity, not a problem with the timer. DosSleep is used solely as a convenient method of displaying the capabilities of the driver.

To run the timer program, use the following command-line:

```
TIMER program_name [program_args]
```

For example, to time an OS/2 Directory command, issue the following command.

### OS/2 Programming Guide

Example:
 timer cmd /c dir c:

# Novell NLM Programming Guide

# 40 Creating NetWare 386 NLM Applications

Open Watcom C/C++ supports version 4.0 of the Netware 386 API. We include the following components:

header files Header files for the Netware 4.0 API are located in the \WATCOM\NOVH directory.

import libraries

Import libraries for the Netware 4.0 API are located in the \WATCOM\NOVI directory.

libraries The C/C++ libraries for Netware 4.0 is located in the \WATCOM\LIB386 and

\WATCOM\LIB386\NETWARE directories.

Servers for remote debugging of Netware 4.0 NLMs are located in the \WATCOM\NLM

directory. The same directory also contains the Open Watcom Execution Sampler for

NLMs.

Applications built for version 4.0 will run on 4.1. We do not include support for any API specific to version 4.1. Netware developers must use the support included with Open Watcom C/C++ version 10.0 or greater since the version supplied by Novell only works with Open Watcom C/C++ version 9.5. Netware 4.1 support requires modification to the header files supplied by Novell. Contact Novell for more information.

The following special notes apply to developing applications for NetWare.

- You must compile your source files with the "-bt=NETWARE" option. This will cause the compiler to:
  - use the small memory model instead of the flat memory model,
  - use stack-based calling conventions,
  - search the NETWARE\_INCLUDE environment variable before searching the **INCLUDE** environment variable, and
  - reference a special startup symbol, \_\_\_WATCOM\_Prelude, in the libraries.
- You must compile your source files with the small memory model option ("ms"). This is accomplished by specifying the "-bt=NETWARE" option.
- You must compile your source files with one of the stack-based calling convention options ("3s", "4s" or "5s"). This is accomplished by specifying the "-bt=NETWARE" option.
- You must set the **NETWARE\_INCLUDE** environment variable to point to the \WATCOM\NOVH directory. This environment variable will be searched first when you compile with the "-bt=NETWARE" option. Alternatively, you can set the INCLUDE environment variable to include \WATCOM\NOVH before other include directories.
- If you are using the compile and link utility WCL386, you must use the following options: "-l=NETWARE -bt=NETWARE".
- You must specify

```
system NETWARE
```

when linking an NLM. This is automatic if you are using WCL386 and the "-l=NETWARE" option.

7. If you are using other Netware APIs such as NWSNUT, then you must include module and import statements as input to the Open Watcom Linker.

#### Example:

```
module nwsnut
import @%WATCOM%\novi\nwsnut.imp
```

This is done automatically for the C Library (CLIB.IMP). The following import lists have been provided for Netware API libraries.

```
AIO.IMP
APPLETLK.IMP
BSD.IMP
CLIB.IMP
DSAPI.IMP
MATHLIB.IMP
NWSNUT.IMP
SOCKLIB.IMP
STREAMS.IMP
TLI.IMP
```

# Mixed Language Programming

# 41 Inter-Language calls: C and FORTRAN

The purpose of this chapter is to anticipate common questions about mixed-language development using Open Watcom C/C++ and Open Watcom FORTRAN 77.

The following topics are discussed in this chapter:

- Symbol Naming Convention
- Argument Passing Convention
- Memory Model Compatibility
- Integer Type Compatibility
- How do I pass integers from C to a FORTRAN function?
- How do I pass integers from FORTRAN to a C function?
- How do I pass a string from a C function to FORTRAN?
- How do I pass a string from FORTRAN to a C function?
- How do I access a FORTRAN common block from within C?
- How do I call a C function that accepts a variable number of arguments?

# 41.1 Symbol Naming Convention

The symbol naming convention describes how a symbol in source form is mapped to its object form. Because of this mapping, the name generated in the object file may differ from its original source form.

Default symbol naming conventions vary between compilers. Open Watcom C/C++ prefixes an underscore character to the beginning of variable names and appends an underscore to the end of function names during the compilation process. Open Watcom FORTRAN 77 converts symbols to upper case. Auxiliary pragmas can be used to resolve this inconsistency.

Pragmas are compiler directives which can provide several capabilities, one of which is to provide information used for code generation. When calling a FORTRAN subprogram from C, we want to instruct the compiler NOT to append the underscore at the end of the function name and to convert the name to upper case. This is achieved by using the following C auxiliary pragma:

```
#pragma aux ftnname "^";
```

The "A" character tells the compiler to convert the symbol name "ftnname" to upper case; no underscore character will be appended. This solves potential linker problems with "ftnname" since (by C convention) the linker would attempt to resolve a reference to "ftnname\_".

When calling C functions from FORTRAN, we need to instruct the compiler to add the underscore at the end of the function name, and to convert the name to lower case. Since the FORTRAN compiler automatically converts identifiers to uppercase, it is necessary to force the compiler to emit an equivalent lowercase name. Both of these things can be done with the following FORTRAN auxiliary pragma:

```
*$pragma aux CNAME "!_"
```

There is another less convenient way to do this as shown in the following:

```
*$pragma aux CNAME "cname_"
```

In the latter example, the case of the name in quotation marks is preserved.

Use of these pragmas resolves the naming differences, however, the issue of argument passing must still be resolved.

# 41.2 Argument Passing Convention

In general, C uses call-by-value (passes argument values) while FORTRAN uses call-by-reference (passes pointers to argument values). This implies that to pass arguments to a FORTRAN subprogram we must pass the addresses of arguments rather than their values. C uses the "&" character to signify "address of".

```
Example:
    result = ftnname( &arg );
```

When calling a C function from FORTRAN, the pragma used to correct the naming conventions must also instruct the compiler that the C function is expecting values, not addresses.

```
*$pragma aux CNAME "!_" parm (value)
```

The "parm (value)" addition instructs the FORTRAN compiler to pass values, instead of addresses.

Character data (strings) are an exception to the general case when used as arguments. In C, strings are not thought of as a whole entity, but rather as an "array of characters". Since strings are not considered scalar arguments, they are referenced differently in both C and FORTRAN. This is described in more detail in a following section.

# 41.3 Memory Model Compatibility

While it is really not an issue with the 32-bit compilers (both use the default "flat" memory model), it is important to know that the default memory model used in Open Watcom FORTRAN 77 applications is the "large" memory model ("ml") with "medium" and "huge" memory models as options. Since the 16-bit Open Watcom C/C++ default is the "small" memory model, you must specify the correct memory model when compiling your C/C++ code with the 16-bit C or C++ compiler.

## 41.4 Linking Considerations

When both C/C++ and FORTRAN object files are combined into an executable program or dynamic link library, it is important that you list a least one of the FORTRAN object files first in the Open Watcom Linker (WLINK) "FILES" directive to guarantee the proper search order of the FORTRAN and C run-time libraries. If you place a C/C++ object file first, you may inadvertently cause the wrong version of run-time initialization routines to be loaded by the linker.

# 41.5 Integer Type Compatibility

In general, the number of bytes used to store an integer type is implementation dependent. In FORTRAN, the default size of an integer type is always 4 bytes, while in C/C++, the size is architecture dependent. The size of an "int" is 2 bytes for the 16-bit Open Watcom C/C++ compilers and 4 bytes for the 32-bit compilers while the size of a "long" is 4 bytes regardless of architecture. It is safest to prototype the function in C, specifying exactly what size integers are being used. The byte sizes are as follows:

- 1. LONG - 4 bytes
- 2. SHORT - 2 bytes

Since FORTRAN uses a default of 4 bytes, we should specify the "long" keyword in C for integer types.

```
Example:
   long int ftnname( long int *, long int *, long int * );
```

In this case, "ftnname" takes three "pointers to long ints" as arguments, and returns a "long int". By specifying that the arguments are pointers, and not values, and by specifying "long int" for the return type, this prototype has solved the problems of argument passing and integer type compatibility.

# 41.6 How do I pass integers from C to a FORTRAN function?

The following Open Watcom C/C++ routine passes three integers to a FORTRAN function that returns an integer value.

```
/* MIX1C.C - This C program calls a FORTRAN function to
             compute the max of three numbers.
 * Compile/Link: wcl /ml mix1c mix1f.obj /fe=mix1
                wcl386 mix1c mix1f.obj /fe=mix1
#include <stdio.h>
#pragma aux tmax3 "^";
long int tmax3( long int *, long int *, long int *);
```

```
void main()
       long int result;
       long int i, j, k;
       i = -1;
       j = 12;
       k = 5;
       result = tmax3( &i, &j, &k );
       printf( "Maximum is %ld\n", result );
The FORTRAN function:
   * MIX1F.FOR - This FORTRAN function accepts three integer
                 arguments and returns their maximum.
   * Compile: wfc[386] mix1f.for
           integer function tmax3( arga, argb, argc )
           integer arga, argb, argc
           tmax3 = arga
           if (argb .gt. tmax3) tmax3 = argb
           if ( argc .gt. tmax3 ) tmax3 = argc
           end
```

# 41.7 How do I pass integers from FORTRAN to a C function?

The following Open Watcom FORTRAN 77 routine passes three integers to a Open Watcom C/C++ function that returns an integer value.

```
* MIX2F.FOR - This FORTRAN program calls a C function to
compute the max of three numbers.

* Compile/Link: wfl[386] mix2f mix2c.obj /fe=mix2

*$pragma aux tmax3 "!_" parm (value)

program mix2f

integer*4 tmax3
integer*4 result
integer*4 i, j, k

i = -1
j = 12
k = 5
result = tmax3(i, j, k)
print *, 'Maximum is', result
end
```

The C function "tmax3" is shown below.

```
/* MIX2C.C - This C function accepts 3 integer arguments
             and returns their maximum.
 * Compile: wcc /ml mix2c
           wcc386 mix2c
 * /
long int tmax3 (long int arga,
                long int argb,
                long int argc )
    long int
               result;
    result = arga;
    if( argb > result ) result = argb;
    if( argc > result ) result = argc;
    return( result );
}
```

# 41.8 How do I pass a string from a C function to FORTRAN?

Character strings are referenced differently in C and FORTRAN. The C language terminates its strings with a null character as an End-Of-String (EOS) marker. In this case, C need not store the length of the string in memory. FORTRAN, however, does not use any EOS marker; hence it must store each string's length in memory.

The structure FORTRAN uses to keep track of character data is called a "string descriptor" which consists of a pointer to the character data (2, 4, or 6 bytes, depending on the data model) followed by an unsigned integer length (2 bytes or 4 bytes, depending on the data model).

option	size of pointer	size of length
/MM	16 bits	16 bits
/ML	32 bits	16 bits
/MF	32 bits	32 bits
/ML	48 bits	32 bits
	/MM /ML /MF	/MM 16 bits /ML 32 bits /MF 32 bits

In order to access character data, FORTRAN needs to have access to the data's string descriptor. Hence, FORTRAN expects a pointer to a string descriptor to be passed as an argument for character data.

Passing string arguments between C and FORTRAN is a simple task of describing a struct type in C containing the two fields described above. The first field must contain the pointer to the character data, and the second field must contain the length of the string being passed. A pointer to this structure can then be passed to FORTRAN.

```
* MIX3F.FOR - This FORTRAN program calls a function written
              in C that passes back a string.
* Compile/Link: wfl[386] mix3f mix3c.obj /fe=mix3
        program mix3f
        character*80 sendstr
        character*80 cstring
```

```
cstring = sendstr()
    print *, cstring(1:lentrim(cstring))
    end
The C function "sendstr" is shown below.
```

# 41.9 How do I pass a string from FORTRAN to a C function?

By default, FORTRAN passes the address of the string descriptor when passing strings. If the C function knows it is being passed a string descriptor address, then it is very similar to the above example. If the C function is expecting normal C-type strings, then a FORTRAN pragma can be used to pass the string correctly. When the Open Watcom FORTRAN 77 compiler pragma to pass by value is used for strings, then just a pointer to the string is passed.

```
Example:
    *$pragma aux cname "!_" parm (value)
```

The following example FORTRAN mainline defines a string, and passes it to a C function that prints it out.

```
* MIX4F.FOR - This FORTRAN program calls a function written
* in C and passes it a string.
*
* Compile/Link: wfl[386] mix4f mix4c.obj /fe=mix4

*$pragma aux cstr "!_" parm (value)

program mix4f

character*80 forstring

forstring = 'This is a FORTRAN string'//char(0)
call cstr( forstring )
end
```

The C function:

```
/* MIX4C.C - This C function prints a string passed from
           FORTRAN.
* Compile: wcc /ml mix4c
     wcc386 mix4c
#include <stdio.h>
void cstr( char *instring )
   printf( "%s\n", instring );
```

#### 41.10 How do I access a FORTRAN common block from within C?

The following code demonstrates a technique for accessing a FORTRAN common block in a C routine. The C routine defines an extern struct to correspond to the FORTRAN common block.

```
* MIX5F.FOR - This program shows how a FORTRAN common
              block can be accessed from C.
* Compile/Link: wfl[386] mix5f mix5c.obj /fe=mix5
        program mix5f
        external put
        common/cblk/i,j
        i = 12
        j=10
        call put
        print *, 'i = ', i
        print *, 'j = ', j
```

The C function:

```
/* MIX5C.C - This code shows how to access a FORTRAN
            common block from C.
* Compile: wcc /ml mix5c
           wcc386 mix5c
*/
#include <stdio.h>
#pragma aux put "^";
#pragma aux cblk "^";
```

```
#ifdef __386__
#define FAR
#else
#define FAR far
#endif

extern struct cb {
    long int i,j;
} FAR cblk;

void put( void )
{
    printf( "i = %ld\n", cblk.i );
    printf( "j = %ld\n", cblk.j );
    cblk.i++;
    cblk.j++;
}
```

For the 16-bit C compiler, the common block "cblk" is described as far to force a load of the segment portion of the address. Otherwise, since the object is smaller than 32K (the default data threshold), it is assumed to be located in the DGROUP group which is accessed through the SS segment register.

# 41.11 How do I call a C function that accepts a variable number of arguments?

One capability that C possesses is the ability to define functions that accept variable number of arguments. This feature is not present, however, in the definition of the FORTRAN 77 language. As a result, a special pragma is required to call these kinds of functions.

```
*$pragma aux printf "!_" parm (value) caller []
```

The "caller" specifies that the caller will pop the arguments from the stack. The "[]" indicates that there are no arguments passed in registers because the printf function takes a variable number of arguments passed on the stack. The following example is a FORTRAN function that uses this pragma. It calls the printf function to print the value 47 on the screen.

For more information on the pragmas that are used extensively during inter-language programming, please refer to the chapter entitled "Pragmas" in both the *Open Watcom C/C++ User's Guide* and the *Open Watcom FORTRAN 77 User's Guide*.

## **Common Problems**

## 42 Commonly Asked Questions and Answers

As with any sophisticated piece of software, there are topics that are not directly addressed by the descriptive portions of the manuals. The purpose of this chapter is to anticipate common questions concerning Open Watcom C/C++. It is difficult to predict what topics will prove to be useful but with that in mind, we hope that this chapter will help our customers make full use of Open Watcom C/C++.

A number of example programs are presented throughout. The source text for these files can be found in the \WATCOM\SAMPLES\GOODIES directory.

The purpose of this chapter is to present some of the more commonly asked questions from our users and the answers to these questions. The following topics are discussed:

- How do I determine my current patch level?
- How do I convert to Open Watcom C/C++?
- What should I know about optimization?
- Why can't the compiler find "stdio.h"?
- How do I resolve an "Undefined Reference" linker error?
- Why aren't my variables set to zero?
- What does "size of DGROUP exceeds 64K" mean for 16-bit applications?
- What does "NULL assignment detected" mean in 16-bit applications?
- What does "Stack Overflow!" mean?
- Why do I get redefinition errors from WLINK?
- How can I open more than 20 files at a time?
- How can I see my source files in the debugger?
- What is the difference between the "d1" and "d2" compiler options?

#### 42.1 Determining my current patch level

In an effort to immediately correct any problems discovered in the originally shipped product, Open Watcom provides patches as a continued service to its customers. To determine the current patch level of your Open Watcom software, a TECHINFO utility program has been provided. This program will display your current environment variables, the patch level of various Open Watcom software programs, and other pertinent information, such as your AUTOEXEC.BAT and CONFIG.SYS files. This information proves to be very useful when reporting a problem to the Technical Support team.

To run TECHINFO, you must ensure the Open Watcom environment variable has been set to the directory where your Open Watcom software has been installed. TECHINFO will pause after each screenful of information. The output is also placed in the file TECHINFO.OUT.

Below is an example of some partial output produced by running the TECHINFO utility:

#### Example: WATCOM's Techin

```
{\tt WATCOM's} Techinfo Utility, Version 1.4
Current Time: Thu Oct 27 15:58:34 1994
WATCOM
                                Phone: (519) 884-0702
415 Phillip St.
                               Fax: (519) 747-4971
Waterloo, Ontario
CANADA
         N2L 3X2
-----WATCOM C Environment Variables ------
WATCOM=<c:\watcom>
EDPATH=<c:\watcom\eddat>
INCLUDE=<c:\watcom\h;c:\watcom\h\os2>
FINCLUDE=<c:\watcom\src\fortran;c:\watcom\src\fortran\win>
LIBOS2=<c:\watcom\lib286\os2;c:\watcom\lib286>
PATH=<c:\dos;c:\windows;c:\watcom\binw>
TMP=<h:\temp>
File 'c:\watcom\binw\wcc386.exe' has been patched to level '.d'
...etc...
```

In this example, the software has been patched to level "d". In most cases, all tools will share a common patch level. However, there are instances where certain tools have been patched to one level while others are patched to a different level. For example, the compiler may be patched to level "d" while the debugger is only patched to level "c". Basically, this means that there were no debugger changes in the D-level patches.

If you run the TECHINFO utility, and determine that you are not at the current patch level, it is recommended that you update your software. Patches are available on Open Watcom's bulletin board, Open Watcom's FTP site and CompuServe. They are available 24 hours a day. Patches are also available on the current release CD-ROM. Each patch will include a batch file that allows you to apply the patches to your existing software. Note that patches must be applied in sequential order, as each patch depends on the previous one.

#### 42.2 Converting to Open Watcom C/C++

There are some common steps involved in converting C programs written for other compilers. Conversion from UNIX and other IBM-compatible PC compilers will be covered in detail later. There are six major problems with most programs that are ported to Open Watcom C/C++. The assumptions that most foreign programs make that may be invalid when using Open Watcom C/C++ are:

- sizeof( pointer ) == sizeof( int )
   (true for 16-bit systems except "far" pointers, true for 32-bit systems except "far" pointers)
- 2. sizeof(long) == sizeof(int)

(not true for 16-bit systems)

3. sizeof( short ) == sizeof( int )

(not true for 32-bit systems)

- 4. arguments are always passed on the stack
- 5. dereferencing the NULL pointer
- 6. "char" is either signed or unsigned

These assumptions are very easy to make when developing programs for only one system. The first point becomes important when you move a program to 80x86 systems. Depending on the memory model, the size of an integer might not equal the size of a pointer. You might ask how this assumption is made in programs. The C language will assume that a function returns an integer unless told otherwise. If a programmer does not declare a function as returning a pointer, the compiler will generate code which would convert an integer to a pointer. On other systems, where the size of an integer is equal to the size of a pointer this would amount to nothing because no conversion was necessary (to change size). The older C compilers did not worry about warning the programmer about this condition and as such this error is imbedded in a lot of older C code. As C was moved to other machines, it became apparent that this assumption was no longer valid for all machines. The 80x86 architecture can have 16-bit integers and 32-bit pointers (in the compact, large, and huge memory models), which means that more care must be taken when working with declarations (converting an int to a 32-bit pointer will result in a segment value of 0x0000 or 0xffff). Similarly, the 386 architecture can have 32-bit integers and 48-bit pointers.

The Open Watcom C/C++ compiler will complain about incorrect pointer and integer mixing thus making programs compiled with Open Watcom C/C++ much more portable. For instance, if the Open Watcom C/C++ compiler complains about your usage of the "malloc" memory allocation function then you probably forgot to include "<stdlib.h>" which contains the prototype of the "malloc" function.

```
Example:
   extern void *malloc( unsigned );
```

The Open Watcom C/C++ compiler was complaining about you trying to assign an integer (the value returned by "malloc") to a pointer. By including the header file with the correct prototype, the Open Watcom C/C++ compiler can validate that you are in fact assigning a pointer value to a pointer.

Passing arguments on the stack has been the method used by most older compilers because it allowed the C library function "printf" to work with a variable number of arguments. Older C compilers catered to a few functions by forcing all the argument handling to be handled by the caller of the function. With the advent of the ANSI (and later ISO) standard, which forced all functions expecting a variable number of arguments to be declared properly, compilers can generate smaller code for routines that did not require a variable number of arguments.

```
Example:
```

```
/* function accepting two arguments */
extern FILE *fopen( char *, char * );
/* function accepting a variable number of arguments */
extern int printf( char *, ...);
```

The Open Watcom C/C++ compiler takes advantage of this part of the ISO/ANSI standard by passing arguments in registers (for the first few arguments). If there are not enough registers for all of the arguments, the rest of the arguments are passed on the stack but the routine being called is responsible for removing them from the stack. By default, the Open Watcom C/C++ compiler uses this calling convention because it results in faster procedure calls and smaller code. The Open Watcom C/C++ calling convention carries with it a responsibility to ensure that all functions are prototyped correctly before they are used. For instance, if a procedure is called with too few arguments, the assumptions that the code generator made (while generating the code) will be invalidated. The code generator assumes that AX (EAX for the 32-bit compiler) and any other registers used to pass arguments will be modified by the called function. The code generator also assumes that the exact amount of arguments pushed on the stack will be removed by the function that is called. It is important to recognize this aspect of the Open Watcom C/C++ compiler because the program will simply not work unless the caller and the function being called strictly agree on the number and types of the arguments being passed. See the "Assembly Language Considerations" chapter in the *Open Watcom C/C++ User's Guide* for more details.

Some compilers allow the NULL pointer to be dereferenced and return NULL (we have never understood the rationale behind this, nor why some compilers continue to support this type of code). Leaving the aesthetics of this type of code behind, using the NULL dereferencing assumption in a program will ensure that the program will not be portable. Source code which contains the NULL dereferencing assumption must be corrected before it will work with Open Watcom C/C++.

Programs that assume that the "char" type is "signed" should use the Open Watcom C/C++ compiler "j" option. The "j" option will indicate to the Open Watcom C/C++ compiler that the "char" type is "signed" rather than the default "unsigned".

#### 42.2.1 Conversion from UNIX compilers

The ISO/ANSI standard for C (which Open Watcom C/C++ adheres to) is very similar to UNIX C. Most of the effort in converting UNIX C programs will involve replacing references to library functions (such as the CURSES library). There are many third-party libraries which are implementations of UNIX libraries on IBM-compatible Personal Computers. There is a common problem which many older UNIX programs exhibit, namely, functions that accept a variable number of arguments are coded in many different ways. Functions accepting a variable number of arguments must be coded according to the ISO standard if they are to work with Open Watcom C/C++. We will code an example of a function which will return the maximum of a list of positive integers.

```
variable number of arguments example
#include <stdarg.h>
int MaxList( int how_many, ... )
    va_list args;
    int max;
    max = 0;
    va_start( args, how_many );
    while ( how_many > 0 ) {
        value = va_arg( args, int );
        if( value > max ) {
            max = value;
    }
    va_end( args );
    return( max );
}
```

Notice that the standard header file STDARG. H must be included in any source file which defines a function that handles a variable number of arguments. The function "MaxList" must be prototyped correctly in other source files external to the source file containing the definition of "MaxList".

```
extern int MaxList( int how_many, ... );
```

See the Open Watcom C Library Reference manual description of "va\_arg" for a more complete description of variable number of arguments handling.

#### 42.2.2 Conversion from IBM-compatible PC compilers

Most of the compilers available for IBM-compatible PCs have been following the ISO/ANSI standard and, as such, the majority of programs will not require extensive source changes. There are problems with programs that use compiler-specific library functions. The use of compiler-specific library functions can be dealt with in two different ways:

- use equivalent Open Watcom C/C++ library functions
- write your own library functions 2.

If portability must be maintained with the other compiler, the predefined macro "\_\_WATCOMC\_\_" can be used to conditionally compile the correct code for the Open Watcom C/C++ compiler.

The default calling convention for the Open Watcom C/C++ compiler is different from the calling convention used by other compilers for Intel-based personal computers. The Open Watcom C/C++ calling convention is different because it will pass some arguments in registers (thus reducing the overhead of a function call) rather than pushing all of the arguments on the stack. The Open Watcom C/C++ compiler is flexible enough to use different calling conventions on a per function basis. Converting code from other compilers usually involves recompiling the C source files and setting up prototypes (to use the older calling convention) for functions written in assembly language. For instance, if you have the functions "video init", "video\_put", and "video\_get" written in assembly language, you can use the following prototypes in any source file which uses these functions.

```
#include <stddef.h>
extern int cdecl video_init( void );
extern void cdecl video_put( int row, int col, char ch, int attr );
extern char cdecl video_get( int row,int col );
```

The inclusion of the STDDEF. H header file defines the "cdecl" calling convention. The Open Watcom C/C++ compiler will ensure that any calls to these three functions will adhere to the "cdecl" calling conventions. The Open Watcom C/C++ compiler will put a trailing underscore "\_" character (as opposed to the beginning of the name for the "cdecl" convention) on any function names to ensure that the program will not link register calling convention calls to "cdecl" convention functions (or vice versa). If the linker indicates that functions defined in assembler files cannot be resolved, it could be a result of not prototyping the functions properly as "cdecl" functions.

*Hint:* (16-bit applications only) Most 16-bit C compilers (including Open Watcom C/C++) have a "large" memory model which means that four byte pointers are used for both code and data references. A subtle point to watch out for involves differences between memory model definitions of different compilers. The "cdecl" calling convention allows functions to assume that the DS segment register points to the group "DGROUP". The Open Watcom C/C++ large memory model has what is called a "floating DS". Any function used for the large memory model cannot assume that the DS segment register points to the group "DGROUP". There are a few possible recourses.

- The assembly code could save and restore the DS segment register and set DS to DGROUP in order to conform to the Open Watcom C/C++ convention. If there are only a few accesses to DGROUP data, it is advisable to use the SS segment register which points to DGROUP in the large memory model.
- The assembly function could be described using a pragma that states that DS should point to "DGROUP" before calling the function.

```
#pragma aux _Setcolor __parm __loadds
```

In the above example, \_Setcolor is the sample function being described.

The final alternative would be the use of the "zdp" compiler option. The "zdp" option informs the code generator that the DS register must always point to "DGROUP". This is the default in the small, medium and flat memory models. Note that "flat" is a 32-bit memory model only.

#### 42.3 What you should know about optimization

The C/C++ language contains features which allow simpler compilers to generate code of reasonable quality. Register declarations and imbedding assignments in expressions are two of the ways that C allows the programmer to "help" the compiler generate good quality code. An important point about the Open Watcom C/C++ compiler is that it is not as important (as it is with other compilers) to "help" the compiler. In order to make good decisions about code generation, the Open Watcom C/C++ compiler uses modern optimization techniques.

*Hint:* The definitive reference on compiler design is the "dragon" book "Compilers - Principles, Techniques, and Tools", Alfred V. Aho, Ravi Sethi, and Jeffrey D. Ullman, published by Addison-Wesley, Reading, Massachusetts, 1986. The authors of the "dragon" book advocate a conservative approach to code generation where optimizations must preserve the semantics of the original program. The conservative approach is used throughout the Open Watcom C/C++ compiler to ensure that programmers can use the compiler without worrying about the semantics of their program being changed. The programmer can request that potentially unsafe optimizations be performed. With regard to the "oa" (ignore aliasing) option provided by the Open Watcom C/C++ compiler, the compiler only ignores aliasing of global variables rather than ignore aliasing totally like other compilers.

There are certain pieces of information which the compiler cannot derive from the source code. The "#pragma" compiler directive is used to provide extra information to the compiler. It is necessary to have a complete understanding of both C/C++ and the machine architecture (i.e., 80x86) before using the powerful pragma compiler directives. See the "Pragmas" chapter in the *Open Watcom C/C++ User's Guide* for more details.

Debugging optimized programs is difficult because variables can be assigned to different locations (i.e., memory or registers) in different parts of the function. The "d2" compiler option will restrict the amount of optimization so that variables occupy one location and can be easily displayed. It follows that the "d2" option is useful for initial development but production programs should be compiled with only the "d1" option for the best code quality. Before you distribute your application to others, you may wish to use the Open Watcom Strip Utility (WSTRIP) to remove debugging information from the executable image on disk thereby reducing disk space requirements.

Hint: The "d2" compiler option will generate symbolic information (for every local variable) and line number information for the source file. The "d1" compiler option will only generate line number information for the source file. The use of these options determines what kind of information will be available for the particular module during the debugging session.

Incorrect programs can sometimes work when compiled with the "d2" option and not work when compiled with the "d1" option. One way this sort of problem arises involves local arrays.

```
void example( void )
    int i;
    int a[10];
    for(i = 0; i \le 10; ++i)
        a[i] = i;
    do_something( a );
}
```

The "for" loop initializes one too many array elements but the version compiled with the "d2" option will overwrite the variable "i" without causing any problems. The same function compiled with the "d1" option would have the variable "i" in a register. The erroneous access of "a[10]" would modify a value that is used to restore a register when the function returns. The register would be "restored" with an incorrect value and this would affect the execution of the function that called this function. The above example shows how a program can work when compiled with the "d2" option and stop working when compiled with the "d1" option. You should always test your program fully with all the modules compiled with the "d1" option to protect yourself from any surprises.

#### 42.4 The compiler cannot find "stdio.h"

The standard header files are usually located in the sub-directory that the Open Watcom C/C++ compiler is installed in. Suppose that the header files are located in the sub-directory c:\watcom\h. If the compiler indicates (through an error message) that it is unable to locate the file STDIO. H, we have forgotten something. There are two ways to indicate to the Open Watcom C/C++ compiler the location of the standard header files.

- 1. use the INCLUDE environment variable
- use the "i" option (Open Watcom C/C++, Open Watcom Compile and Link)

The use of the environment variable is the simplest way to ensure that the include files will be found. For instance, if you include the following line in your system initialization file, AUTOEXEC.BAT,

```
set include=c:\watcom\h
```

the Open Watcom C/C++ compiler will be able to find the standard include files. The use of the "i" option is another way to give the directory name of the standard include files.

#### Example:

```
C>wcc myfile.c -ic:\watcom\h
C>wcc386 myfile.c -ic:\watcom\h
C>wpp myfile.cpp -ic:\watcom\h
    or
C>wpp386 myfile.cpp -ic:\watcom\h
```

The usual manner that these methods are combined is as follows. The **INCLUDE** environment variable is used to give the location of the standard C library header files. Any directories of header files local to a specific programming project are often candidates for the "i" option method. See the "Open Watcom C/C++ #include File Processing" section of the chapter entitled "The Open Watcom C/C++ Compilers" in the *Open Watcom C/C++ User's Guide* for more details.

### 42.5 Resolving an "Undefined Reference" linker error

The Open Watcom Linker builds an executable file by a process of resolving references to functions or data items that are declared in other source files. Certain conditions arise that cause the linker to generate an "Undefined Reference" error message. An "Undefined Reference" error message will be displayed by the linker when it cannot find a function or data item that was referenced in the program. Verify that you have included all the required object modules in the linker command and that you are linking with the correct libraries. There are a couple of "undefined references" that require some explanation.

\_cstart\_

The unresolved reference for \_cstart\_ indicates that the linker cannot find the C/C++ run-time libraries. The 16-bit C run-time libraries for the small memory model are clibs.lib and, either maths.lib, or math87s.lib. The 32-bit C run-time libraries for the flat memory model compiled for the register-based argument passing model are clib3r.lib and, either math3r.lib, or math387r.lib. Ensure that the **WATCOM** environment variable is set to the directory that Open Watcom C/C++ was installed in.

fltused

The fltused undefined reference indicates that floating-point arithmetic has been used in the modules that exhibit this error. The remedy is to ensure that the linker can find the appropriate math library. For the 16-bit small memory model, it is either maths.lib, or math87s.lib For the 32-bit register-based argument passing model, it is either math3r.lib, or math387r.lib depending on which floating-point option is used. Ensure that the WATCOM environment variable is set to the directory that Open Watcom C/C++ was installed in.

\_small\_code\_ If this undefined reference occurs when you are trying to create a 16-bit application, we have saved you many hours of debugging! The reason for this undefined reference is that the "main" entry point has been compiled for a big code model (in any one of medium, large, or huge memory models). Any of the modules that have this undefined reference have been compiled for a small code model (in any one of small or compact memory models) and as such do not have the correct return instructions. You should recompile the modules so that all the modules are compiled for the same memory model. Combining

source modules compiled for different memory models is very difficult and often leads to strange bugs. If your program has special considerations and this reference causes you problems, there is a "work-around". You could resolve the reference with a PUBLIC declaration in an assembler file or code the following in Open Watcom C/C++.

```
/* rest of your module */
void _small_code( void )
{ }
```

The code generator will generate a single RET instruction with the public symbol small code attached to it. The common epilogue optimizations will probably combine this function with another function's RET instruction and you will not even pay the small penalty of one byte of extra code.

There may be another cause of this problem, the "main" function must be entered in lower case letters ("Main" or "MAIN" are not identified as being the same as "main" by the compiler). The compiler will identify the module that contains the definition of the function "main" by creating the public definition of either \_small\_code\_ or \_big\_code\_ depending on the memory model it was compiled in.

\_big\_code\_

Your module that contains the "main" entry point has been compiled with a 16-bit small code model (small or compact). The modules that have this undefined reference have been compiled in 16-bit big code models (medium, large, or huge). You should recompile the modules so that all the modules are compiled in the same memory model. See the explanation for \_small\_code\_ for more details.

main

All C programs, except applications developed specifically for Microsoft Windows, must have a function called "main". The name "main" must be in lower case for the compiler to generate the appropriate information in the "main" module.

**WINMAIN** 

All Windows programs must have a function called "WinMain". The function "WinMain" must be declared "pascal" in order that the compiler generate the appropriate name in the "WinMain" module.

#### 42.6 Why my variables are not set to zero

The linker is the program that handles the organization of code and data and builds the executable file. C guarantees that all global and static uninitialized data will contain zeros. The "BSS" region contains all uninitialized global and static data for C programs (the name "BSS" is a remnant of the early UNIX C compilers). Most C compilers take advantage of this situation by not explicitly storing all the zeros to achieve smaller executable file sizes. In order for the program to work correctly, there must be some code (that will be executed before "main") that will clear the "BSS" region. The code that is executed before "main" is called "startup" code. The linker must indicate to the startup code where the "BSS" region is located. In order to do this, the Open Watcom Linker (WLINK) treats the "BSS" segment (region) in a special manner. The special variables '\_edata' and '\_end' are constructed by the Open Watcom Linker so that the startup code knows the beginning and end of the "BSS" region.

Some users may prefer to use the linker provided by another compiler vendor for development. In order to have the program execute correctly, some extra care must be taken with other linkers. For instance, with the Microsoft linker (LINK) you must ensure that the '/DOSSEG' command line option is used. With the Phar Lap Linker, you must use the "-DOSORDER" command line option. In general, if you must use other linkers, extract the module that contains \_cstart from clib?.lib(? will change depending on the

memory model) and specify the object file containing \_cstart as the first object file to be processed by the linker. The object file will contain the information necessary for the linker to build the executable file correctly.

### 42.7 What does "size of DGROUP exceeds 64K" mean for 16-bit applications?

This question applies to 16-bit applications. There are two types of segments in which data is stored. The two types of segments are classified as "near" and "far". There is only one "near" segment while there may be many "far" segments. The single "near" segment is provided for quick access to data but is limited to less than 64K in size. Conversely, the "far" segments can hold more than 64K of data but suffer from a slight execution time penalty for accessing the data. The "near" segment is linked by arranging for the different parts of the "near" segment to fall into a group called DGROUP. See the section entitled "Memory Layout" in the *Open Watcom Linker User's Guide* for more details.

The 8086 architecture cannot support segments larger than 64K. As a result, if the size of DGROUP exceeds 64K, the program cannot execute correctly. The basic idea behind solving this problem is to move data out of the single "near" segment into one or more "far" segments. Of course, this solution does not come without any penalties. The penalty is paid in decreased execution speed as a result of accessing "far" data items. The magnitude of this execution speed penalty depends on the behavior of the program and, as such, cannot be predicted (i.e., we cannot say that the program will take precisely 5% longer to execute). The specific solution to this problem depends on the memory model being used in the compilation of the program.

If you are compiling with the tiny, small, or medium memory models then there are two possible solutions. The first solution involves changing the program source code so that any large data items are declared as "far" data items and accessed with "far" pointers. The addition of the "far" keyword into the source code makes the source code non-portable but this might be an acceptable tradeoff. See the "Advanced Types" chapter in the Open Watcom C Language Reference manual for details on the use of the "near" and "far" keywords. The second solution is to change memory models and use the large or compact memory model. The use of the large or compact memory model allows the compiler to use "far" segments to store data items that are larger than 32K.

The large and compact memory models will only allocate data items into "far" segments if the size of the data item exceeds 32K. If the size of DGROUP exceeds 64K then a good solution is to reduce the size threshold so that smaller data items will be stored into "far" segments. The relevant compiler option to accomplish this task is "zt<num>". The "zt" option sets a data size threshold which, if exceeded, will allocate the data item in "far" segments. For instance, if the option "zt100" is used, any data item larger than 100 bytes will be allocated in "far" segments. A good starting value for the data threshold is 32 bytes (i.e., "zt32"). The number of compilations necessary to reduce the size of DGROUP for a successful link with WLINK depends on the program. Minimally, any files which allocate a lot of data items should be recompiled. The "zt<num>" option should be used for all subsequent compiles, but the recompilation of all the source files in the program is not necessary. If the "DGROUP exceeds 64K" WLINK error persists, the threshold used in the "zt<num>" option should be reduced and all of the source files should be recompiled.

### 42.8 What does "NULL assignment detected" mean in 16-bit applications?

This question applies to 16-bit applications. The C language makes use of the concept of a NULL pointer. The NULL pointer cannot be dereferenced according to the ISO standard. The Open Watcom C/C++ compiler cannot signal the programmer when the NULL address has been written to or read from because the Intel-based personal computers do not have the necessary hardware support. The best that the run-time system can do is help programmers find these sorts of errors through indirect means. The lower 32 bytes of "near" memory have been seeded with 32 bytes of the value 0x01. The C run-time function "\_exit" checks these 32 bytes to ensure that they have not been written over. Any modification of these 32 bytes results in the "NULL assignment error" being printed before the program terminates.

Here is an overview of a good debugging technique for this sort of error:

- use the Open Watcom Debugger to debug the program
- 2. let the program execute
- find out what memory has been incorrectly modified
- set a watchpoint on the modified memory address
- restart the program with the watchpoint active
- let the program execute, for a second time
- when the memory location is modified, execution will be suspended

We will go through the commands that are executed for this debugging session. First of all, we invoke the Open Watcom Debugger from the command line as follows:

```
C>wd myprog
```

Once we are in the debugger type:

```
DBG>qo
```

The program will now execute to completion. At this point we can look at the output screen with the debugger command, "FLIP".

```
DBG>flip
```

We would see that the program had the run-time error "NULL assignment detected". At this point, all we have to do is find out what memory locations were modified by the program.

The following command will display the lower 16 bytes of "near" memory.

```
DBG>examine __nullarea
```

The command should display 16 bytes of value 0x01. Press the space bar to display the next 16 bytes of memory. This should also display 16 bytes of value 0x01. Notice that the following data has two bytes which have been erroneously modified by the program.

```
01 01 56 12 01 01 01 01-01 01 01 01 01 01 01 01
nullarea
```

The idea behind this debugging technique is to set a watchpoint on the modified memory so that execution of the program will be suspended when it modifies the memory. The following command will "watch" the memory for you.

```
DBG>watch __nullarea+2
```

There has to be a way to restart the program without leaving the Open Watcom Debugger so that the watchpoint is active during a subsequent execution of the program. The Open Watcom Debugger command "NEW" will reload the program and prepare for a new invocation of the program.

```
DBG>new
DBG>go
```

The Open Watcom Debugger command "GO" will start execution of the program. You may notice that the program executes much slower than usual but eventually the debugger will show the part of the program that modified the two bytes. At this point, you might want to clear the watchpoint and proceed to debug why the memory was modified. The command to clear the watchpoint is:

```
DBG>watch/clear 1
```

The "1" indicates that you want watchpoint number 1 to be cleared. Typing "WATCH" by itself will print out all active watchpoints. The above technique is generally useful for any type of memory overwrite error provided you know which memory location has been overwritten.

Hint: The Open Watcom Debugger allows many commands to have short forms. For instance, the "EXAMINE" command can be shortened to an "E". We used the full commands in the examples for clarity.

#### 42.9 What "Stack Overflow!" means

The memory used for local variables is allocated from the function call stack although the Open Watcom compilers will often use registers for local variables. The size of the function call stack is limited at link-time and it is possible to exceed the amount of stack space during execution. The Open Watcom run-time library will perform checks whenever a large amount of stack space is required by a function but it is up to the user to check stack requirements before calling a Open Watcom run-time function. Compiling programs with stack checking will ensure that there is enough stack space to call a Open Watcom run-time function.

There are various ways of protecting against stack overflow errors. First, one should minimize the number of recursive functions used in an application program. This can be done by recoding recursive functions to use loops. Keep the amount of stack used in functions to a minimum by using and reusing static arrays whenever possible. These techniques will reduce the amount of stack space required but there still may be times where the default amount of stack space is insufficient. The Open Watcom Linker (WLINK) allows the user to set the amount of stack space at link-time through the directive "OPTION STACK=size" where size may be specified in bytes with an optional "k" suffix for kilobytes (1024 bytes).

```
Example:
    option stack=9k
```

Debugging a program that reports a stack overflow error can be accomplished with the following sequence.

- Load your application into the debugger
- 2. Set a breakpoint at \_\_\_STKOVERFLOW
- 3. Run the application until the breakpoint at \_\_\_STKOVERFLOW is triggered
- Issue the debugger "show calls" command. This will display a stack traceback giving you the path of calls that led up to the stack overflow situation.

The solution to the stack overflow problem at this point depends on the programmer.

### 42.10 Why redefinition errors are issued from WLINK

This question comes up often in discussions about porting old UNIX or Microsoft C programs. The problem stems from the forgiving nature of early UNIX linkers. In early C code, it was common to define header files like this:

```
Example:
   /* define global variables */
   int line_count;
   int word_count;
   int char_count;
```

The header file would then be included in many different modules. The C compiler would generate a definition of each variable in each module and leave it to the linker to pick one and resolve all references to one variable. The development of the ANSI C standard made this practice non-conforming. The Open Watcom C compiler is an ISO/ANSI C compiler and as such, is not required to support this obsolete behavior. The effect is that WLINK will report redefinition errors. The header file must be coded in such a way that the variables are defined in one module. One way to do this is as follows:

#### Example:

```
#ifdef DEFINE HERE
#define GLOBAL
#else
#define GLOBAL extern
#endif
/* define global variables */
GLOBAL int line_count;
GLOBAL int word_count;
GLOBAL int char_count;
```

In most modules, the macro "DEFINE\_HERE" will not be defined so the file will be equivalent to:

#### Example: /\* define global variables \*/ extern int line\_count; extern int word\_count; extern int char\_count;

In one module, the macro "DEFINE\_HERE" must be defined before the header file is included. This can be done by defining the macro on the command line or by coding like this:

```
Example:
   #define DEFINE_HERE
   #include "globals.h"
```

#### 42.11 How more than 20 files at a time can be opened

The number of file handles allowed by Open Watcom C/C++ is initialized to 20 in stdio.h, but this can be changed by the application developer. To change the number of file handles allowed with Open Watcom C/C++, follow the steps outlined below.

- Let n represent the number of files the application developer wishes to have open. Ensure that the stdin, stdout, stderr, stdaux, and stdprn files are included in the count.
- Change the CONFIG. SYS file to include "files=n" where "n" is the number of file handles required by the application plus an additional 5 handles for the standard files (this applies to DOS 5.0). The number "n" may vary depending on your operating system and version. If you are running a network such as Novell's NetWare, this will also affect the number of available file handles. In this case, you may have to increase the number specified in the "files=n" statement.
- Add a call to \_grow\_handles in your application.

The following example illustrates the use of \_grow\_handles.

```
Example:
       HANDLES.C
       This C program grows the number of file handles so
      more than 16 files can be opened. This program
       illustrates the interaction between _grow_handles and
    ^{\star} the DOS 5.0 file system. If you are running a network
    * such as Novell's NetWare, this will also affect the
    * number of available file handles. In the actual trial,
       FILES=40 was specified in CONFIG.SYS.
```

```
#include <stdio.h>
void main()
           i, j, maxh, maxo;
    int
    FILE
         *temp_files[50];
    for(i = 25; i < 40; i++) {
        /* count 5 for stdin, stdout, stderr, stdaux, stdprn */
        printf( "Trying for %2.2d handles...", 5 + i );
        maxh = \_grow\_handles(5 + i);
        maxo = 0;
        for( j = 0; j < maxh; j++ ) {
            temp_files[j] = tmpfile();
            if( temp_files[j] == NULL )break;
            maxo++;
        printf( " %d/%d temp files opened\n", maxo, maxh );
        for(j = 0; j < maxo; j++) {
            fclose( temp_files[j] );
    }
}
```

#### 42.12 How source files can be seen in the debugger

The selection and use of debugging information is important for getting the most out of the Open Watcom Debugger. If you are not able to see your source code in the Open Watcom Debugger source window, there are three areas where things may have gone wrong, namely:

- using the correct option for the Open Watcom C/C++.
- using the correct directives for the Open Watcom Linker.
- using the right commands in the Open Watcom Debugger.

The Open Watcom C/C++ compiler takes C/C++ source and creates an object file containing the generated code. By default, no debugging information is included in the object file. The compiler will output debugging information into the object file if you specify a debugging option during the compile. There are two levels of debugging information that the compiler can generate:

- Line numbers and local variables ("d2" option) 1.
- 2. Line numbers ("d1" option)

The options are used to determine how much debugging information will be visible when you are debugging a particular module. If you use the "d2" option, you will be able to see your source file and display your local variables. The "d1" option will display the source but will not give you access to local variable information.

The Open Watcom Linker (WLINK) is the tool that puts together a complete program and sets up the debugging information for all the modules in the executable file. There is a linker directive that indicates to the linker when it should include debugging information from the modules. There are five levels of debugging information that can be collected during the link. These are:

global names (DEBUG)

- global names, line numbers (DEBUG LINE)
- 3. global names, types (DEBUG TYPES)
- 4. global names, local variables (DEBUG LOCALS)
- all of the above (DEBUG ALL)

Notice that global names will always be included in any request for debugging information. The debugging options can be combined

```
DEBUG LINE, TYPES
```

with the above directive resulting in full line number and typing information being available during debugging. The directives are position dependent so you must precede any object files and libraries with the debugging directive. For instance, if the file mylink.lnk contained:

```
invoke with: wlink @mylink
file main
debug line
file input, output
debug all
file process
```

then the modules input and output will have global names and source line information available during debugging. All debugging information in the module process will be available during debugging.

*Hint:* A subtle point to debugging information is that all the modules will have global names available if any debugging directive is used. In the above example, the module main will have global name information even though it does not have a DEBUG directive preceding it.

It is preferable to have one DEBUG directive before any FILE and LIBRARY directives. You might wonder if this increases the size of the executable file so that it will occupy too much memory during debugging. The debugging information is loaded "on demand" by the debugger during the debugging session. A small amount of memory (40k default, selectable with the Open Watcom Debugger "dynamic" command line option) is used to hold the most recently used module debugging information. In practice, this approach saves a lot of memory because most debugging information is never used. The overhead of accessing the disk for debugging information is negligible compared to accessing the source file information. In other words, you can have as much debugging information as you want included in the executable file without sacrificing memory required by the program. See the section entitled "The DEBUG Directive" in the *Open Watcom Linker User's Guide* for more details.

If the previous steps have been followed, you should be well on your way to debugging your programs with source line information. There are instances where the Open Watcom Debugger cannot find the appropriate source file even though it knows all the line numbers. The problem that has surfaced involves how the source file is associated with the debugging information of the module. The original location of the source file is included in the debugging information for a module. The name that is included in the debugging information is the original name that was on the Open Watcom C/C++ command line. If the original filename is no longer valid (i.e., you have moved the executable to another directory), the Open Watcom Debugger must be told where to find the source files. The Open Watcom Debugger "Source Path" menu item (under "File") can be used to supply new directories to search for source files. If your source files are located in two directories, the following paths can be added in the Open Watcom Debugger:

```
c:\program\c\*.c
c:\program\new\c\*.c
```

The "\*" character indicates where the module name will be inserted while the Open Watcom Debugger is searching for the source file. See the description of the "Source Path" menu item in the *Open Watcom* **Debugger User's Guide** for more details.

### 42.13 The difference between the "d1" and "d2" compiler options

The reason that there are two levels of debugging information available is that the code optimizer can perform many more optimizations and still maintain "d1" (line) information. The "d2" option forces the code optimizer to ensure that any local variable can be displayed at any time in the function. To illustrate why this results in less optimum code being generated for a function, let us look at a simple array initialization.

```
extern int a[100];
void init_a( void )
    int i;
    for(i = 0; i < 100; ++i) {
       a[i] = 3*i;
    }
}
```

The code optimizer will ensure that you can print the value of the variable "i" at any time during the execution of the loop. The "d2" option will always generate code and debugging information so that you can print the value of any variable during the execution of the function. In order to get the best code possible and still see your source file while debugging, the "d1" option only generates line number information into the object file. With line number information, much better code can be generated. Here is the C equivalent of the code generated for the array initialization example.

```
extern int a[100];
void init_a( void )
    int *t1;
    int t2;
    /* for ( i = 0; i < 100; ++i ) { */
    t1 = a;
    t2 = 0;
    do {
         /* a[i] = 3*i; */
        *t1 = t2;
        ++t1;
        t2 += 3;
    /* } */
    } while ( t1 != a + 100 );
}
```

The above code executes very quickly but notice that the variable "i" has been split into two different variables. One of the variables handles the use of "i" as an array index and the other handles the calculation of "3\*i". The debugging of programs that have undergone extensive optimization can be difficult, but with the source line information it is much easier. To summarize, use the "d2" compiler option if you are developing a module and you would like to be able to display each local variable. The "d1" compiler option will give you line number information and the best generated code possible. There is absolutely no reason not to specify the "d1" option because the code quality will be identical to code generated without the "d1" option.

#### 1

16-bit 139
16-bit DLL 165
16-bit DOS applications 5
16-bit far pointer 139
16-bit near pointer 139
16-bit OS/2 1.x applications 239
16-bit Windows 3.x application 121
16-bit Windows 3.x applications 121
16-bit Windows 3.x non-GUI applications 125
\_16xxx functions 205

#### 3

32-bit 139
32-bit DLL 157, 165
32-bit DOS/4GW applications 13
32-bit far pointer 139
32-bit gates 58
32-bit near pointer 139
32-bit OS/2 applications 243
32-bit Phar Lap 386|DOS-Extender applications 9
32-bit Windows 3.x application 129
32-bit Windows 3.x applications 129
32-bit Windows 3.x non-GUI applications 133
386enh 144
386LINK 289



4GWPRO.EXE 114



8042 auxiliary processor 51

#### A

A000 201 A20 line 51-52 address line 20 52 AllocAlias16 172, 147, 173, 179, 190, 199 AllocHugeAlias16 173, 147, 173, 180, 190 answers to general problems 281 API special functions 205 application development 1 arguments what you need to know 283 array subscript errors how they hurt 287 AUTOEXEC.BAT system initialization file 287 autopassup range 58 auxiliary pragma loadds 286



\_\_B000 201 B800 201 BBS 282 beginthread function 222, 248 bi-modal interrupt 33 \_big\_code\_ 289 binding 32-bit applications 130, 135 binding a 32-bit DLL 131, 135 BINP directory 241 BINW directory 131, 136 BSS segment 289 building 386|DOS-Extender applications 9 building DOS applications 5 building DOS/4GW applications 13 building OS/2 1.x applications 240 building OS/2 applications 244 building Windows 3.x applications 122, 130 building Windows NT applications 213, 217 bulletin board 282

	debugging DOS applications 6
<u>C</u>	debugging DOS/4GW applications 14
	debugging information
	global variables 295
	line numbering 295
C000 201	local variables 295
<del></del>	Open Watcom C/C++ 295
_Call B A CKDTP 202	Open Watcom Debugger 296
CALLBACKPTR 203	source file 295
calling convention	types 295
what you need to know 283	WLINK 295
calling conventions	debugging Non-GUI 16-bit Windows 3.x applications
cdecl 285	127
Catch 144	debugging Non-GUI 32-bit Windows 3.x applications
cdecl 152, 174, 177, 233	136
calling convention 285	debugging OS/2 1.x applications 240
class 145	debugging OS/2 applications 244
clearing	
variables 289	debugging Windows 3.x applications 122, 131
COMMDLG.H 144	debugging Windows NT applications 214, 218
common questions 281	default windowing library functions 128, 137
DOS/4GW 103	DefineDLLEntry 176
Compaq 386 memory 50	DefineUserProc16 <b>177</b> , 186
compile options	DELETESWAP virtual memory option 53, 112-113
zdp 286	DevHlp 263
CompuServe 282	device driver header 262
CONFIG.SYS 241, 263	DEVICE= 263
const 171	DGROUP size exceeds 64K 290
converting to Open Watcom C/C++ 282	distribution rights 144
common problems 282	DLL 261
from IBM-compatible PC compilers 285	16-bit 165
from UNIX 284	16-bit calls into 32-bit DLLs 160
what you need to know 282	16-bit cover 161
_cstart_ 288	32-bit 157, 165
CUSTCNTL.H 144	32-bit Windows example 158
COSTCNIL.II 144	creating 162-163
	debugging 162
	debugging example 163
ח	installing example 163
<i>D</i>	OS/2 2.x 251
	running example 163
	summary 164
D000 201	Windows NT 225
d1 287	DLL access
d1 versus d2 297	OS/2 2.x 254
d2 287	Windows NT 229
DDE.H 144	DLL creation
DDEML.H 144	OS/2 2.x 251
debugging 287	Windows NT 225
memory bugs 291	DLL directory 241
NULL assignment detected 291	DLL initialization
optimized programs 287, 297	OS/2 2.x 255
stack overflow 292	DLL sample
techniques 291-292	OS/2 2.x 252
debugging 386 DOS-Extender applications 10	Windows NT 226

DLL termination	NULL pointer references 108
OS/2 2.x 255	OS/2 bug 118
DLL_CHAR 176	out of memory 112
DLL_DWORD 176	pointers vs linear addresses 107
DLL_ENDLIST 176	realloc 110
dll_initialize 256	register dump 115
DLL_PTR 176	runtime options 51
dll_terminate 256	spawning 111
DLL_WORD 176	switch mode setting 48
DOS extenders	TCPIP.EXE 118
common problems 17	telephone support 104
DOS file I/O 111	transfer stack overflow 115
DOS memory 24	TSR not supported 41
using DOS/4GW 24	unexpected interrupt 114
using Phar Lap 25	utilities 87
DOS memory management 67	VESA support 111
DOS Protected-Mode Interface 61	VM configuration 113
DOS/4GW	VMM 111
4GWPRO.EXE 114	VMM instability 112
address line 20 52	VMM restriction 41
asynchronous interrupts 108	Windows NT bug 118
bi-modal interrupt 33	DOS/4GW DOS extender 41
cannot lock stack 118	DOS/4GW DOS extender 41 DOS16M
chaining handlers 59	+ option 50
code and data addresses 107	A20 option 52
common questions 103	loops option 52
contacting Tenberry 104	runtime options 51
Ctrl-Break handling 109	DOS16M environment variable 47-52, 91
debugger version 114	DOS4G
debugging bound applications 114	NULLP option 47, 108
demand-loading 112	QUIET option 47
differences with DOS/4G 105	VERBOSE option 47, 115
differences with Professional version 104	DOS4G environment variable 47
documentation 104	DOS4GPATH environment variable 43
DOS file I/O 111	DOS4GVM
DOSX.EXE 118	DELETESWAP 112-113
DPMI support 106	MAXMEM 113
EMM386.EXE 117	MINMEM 113
error messages 98	SWAPINC 112-113
extender messages 95	SWAPMIN 112-113
extra memory 50	SWAPNAME 112
int 70h-77h 109	VIRTUALSIZE 112-113
interrupt handler address 59	DOS4GVM environment variable 53-54
interrupt handlers 59, 109	DOS4GVM.SWP 53
kernel error messages 95	DOS4GW 88
linear vs physical addresses 107	DOS4GW.EXE 43
locking memory 109	DosFreeModule 252
Lotus 1-2-3 117	DosLoadModule 252-253
low memory access 107	DosSleep 263
memory addressability 111	DOSX.EXE 118
memory control 49	DPMI 50, 58, 61
memory range 49	allocate DOS memory block 67
memory use 44	allocate memory block 80
mouse support 111	allocate real-mode callback address 74

demand paging 81	dynamic link library 157, 165
discard page 82	dynamic link library access
free DOS memory block 68	OS/2 2.x 254
free memory block 80	Windows NT 229
free physical address mapping 83	dynamic link library creation
free real-mode callback address 78	OS/2 2.x 251
function calls 62	Windows NT 225
get and disable virtual interrupt state 84	dynamic link library initialization
get and enable virtual interrupt state 84	OS/2 2.x 255
get API entry point 85	dynamic link library sample
get coprocessor status 85	OS/2 2.x 252
get DPMI version 78	Windows NT 226
get exception handler vector 69	dynamic link library termination
get free memory information 79	OS/2 2.x 255
get page size 81	dynamic linking 225, 251
get protected-mode interrupt vector 70	dynamic mixing 223, 231
get real-mode interrupt vector 69	
get virtual interrupt state 84	
lock linear region 81	E
mark page 81	-
physical address mapping 82	
resize DOS memory block 68	
resize memory block 80	E000 201
set coprocessor emulation 86	EMM386.EXE 117
set exception handler vector 69	_endthread function 222, 248
set protected-mode interrupt vector 70	EnumChildWindows 185
set real-mode interrupt vector 69	EnumFonts 185
simulate real-mode far call 73	EnumMetaFile 185
simulate real-mode interrupt 72	EnumObjects 185
simulate real-mode interrupt 72	EnumProps 185
unlock linear region 81	enums 211
vendor extensions 85	EnumTaskWindows 186
virtual interrupt state 83	EnumWindows 186
DPMI host	environment variables
386Max 61	DOS16M 47-52, 91
OS/2 VDM 61	DOS4G 47
QEMM QDPMI 61	DOS4GPATH 43
Windows 3.1 61	DOS4GVM 53-54
DPMI specification 17, 23, 104	INCLUDE 165, 224, 249, 267, 287-288
DPMI_MEMORY_LIMIT	NETWARE_INCLUDE 267
DOS setting 118	PATH 131, 135-136, 165
dragon book 286	WATCOM 131, 135-136, 223, 249, 288
DRIVINIT.H 144	WINDOWS_INCLUDE 165, 170
DS segment register 286	errno 171
_dwDeleteOnClose 128, 137	error messages
DWORD 152, 203	DOS/4GW 98
_dwSetAboutDlg 128, 137	kernel 95
_dwSetAppTitle 128, 137	example
_dwSetConTitle 128, 137	variable number of arguments 284
_dwShutDown 128, 137	EXE header 262
_dwYield 128, 138	executable
dynamic link libraries 241	linear 43
OS/2 2.x 251	segmented 43
Windows NT 225	

GETPROC LINEDDA 186 executable file 6, 10, 14, 122, 127, 130, 135, 214, 218, 240, 244 GETPROC\_SETRESOURCEHANDLER 186 extended memory 47 **GETPROC SETTIMER 186** extender messages GETPROC\_SETWINDOWSHOOK 186 DOS/4GW 95 GETPROC USERDEFINED 1 177 GETPROC\_USERDEFINED\_32 177 GETPROC USERDEFINED x 186 GetProcAddr 198 F GetProcAddress 152, 174, 197 GlobalAlloc 148 GlobalLock 198-199 GlobalNotify 186 F000 201 **GMEM DDESHARE 148** far 139-140, 144, 186, 278 GrayString 186 far pointer 139 \_grow\_handles 294 files GWL\_WNDPROC 151 more than 20 294 unable to find 287 \_fltused\_ 288 free 148, 183 free memory 19 using DOS/4GW 20 using Phar Lap 21 using Windows 3.x 22 FreeAlias16 179, 147 device driver 262-263 EXE 262 FreeHugeAlias16 **180**, 180 FreeIndirectFunctionHandle 181, 174, 183, 197-198 header files 287 FreeLibrary 228 \_HEADER 261 FreeProcInstance 150 hello program 5, 9, 13, 239, 243 FTP site 282 HIMEM.SYS 51 Fujitsu FMR-70 switch mode setting 48 HINDIR 203 Hitachi B32 switch mode setting 48 HRTEST.EXE 263 HRTIMER.SYS 261 G GetIndirectFunctionHandle 183, 174, 181, 188, 197-198 GetLastError 228 GetModuleFileName 227 i8253 timer 263 IBM PS/55 switch mode setting 48 GetProc16 **185**, 146, 148, 177, 195, 198 GETPROC\_ABORTPROC 185 IBM-compatible PC compilers 285 GETPROC\_CALLBACK 185 IDT 58 GETPROC ENUMCHILDWINDOWS 185 import 268 **GETPROC ENUMFONTS 185** import definitions 225, 251 GETPROC ENUMMETAFILE 185 import library 229, 254 INCLUDE environment variable 165, 224, 249, 267, GETPROC\_ENUMOBJECTS 185 GETPROC ENUMPROPS FIXED DS 185 287-288 GETPROC\_ENUMPROPS\_MOVEABLE\_DS 185 INDIR\_CDECL 183 GETPROC ENUMTASKWINDOWS 186 **INDIR CHAR 183 GETPROC ENUMWINDOWS 186 INDIR DWORD 183** GETPROC\_GLOBALNOTIFY 186 **INDIR ENDLIST 183** GETPROC\_GRAYSTRING 186 INDIR\_PTR 183, 188

INDIR WORD 183 loadds pragma option 286 \_INITCODE 261 LoadLibrary 197, 227-228 INITDATA 261 local descriptor table 62 **INITGLOBAL 262** LocalAlloc 148 initialization LocalLock 146 OS/2 2.x dynamic link library 255 LocalPtr 201 initialized global data 289 longjmp 144 Instant-D 43 Lotus 1-2-3 117 int 140 LZEXPAND.H 144 INT 21H 55 INT 31H 21, 61 int 31H function calls 62 М INT 33H using DOS/4GW 28 integer/pointer equivalence 283 inter-language calls 271 macros interrupt handling 58 \_\_WATCOMC\_\_ 285 interrupt services 69 main 289 interrupts MakeProcInstance 148, 150 real-mode simulation 32 malloc 148, 183 invalid conversion 283 MapAliasToFlat 190 InvokeIndirectFunction 188, 183, 197-198 MAXMEM virtual memory option 53, 113 InvokeIndirectFunctionHandle 174 memory management services 79 iostream 5, 9, 13, 126, 134, 239, 243 memory models ISO/ANSI standard what you need to know 283 NULL 291 memory transfer rate 89 variable number of arguments 283 memory wait states 89 message header files 287 unable to find files 287 Κ undefined references 288 MessageBox 121, 129, 213 messages kernel error messages 95 DOS/4GW 95 keyboard status 51 Microsoft LINK 289 LINK386 289 Microsoft Win32 SDK 233 MINMEM virtual memory option 53, 113 mixed-language programming 271 argument passing 272 common blocks 277 LDT 62 integer type 273 LE format 43 linking issues 273 LibMain 227-228, 252-253 memory models 272 library functions parameter passing 272 default windowing 128, 137 passing integers 273-274 line number information 287 passing strings 275-276 linear executable 43 symbol names 271 LineDDA 186 variable number of arguments 278 LINK 289 MK\_FP16 **191**, 155, 199 LINK386 289 MK\_FP32 192, 140, 146, 154, 176, 191, 199 MK\_LOCAL32 **193**, 146, 154-155

undefined references 288

MMSYSTEM.H 144	calling convention 283
mode switching	converting to 282
basis 92	unique aspects 283
performance 89	Open Watcom C/C++ options
module 268	d1 287, 295, 297
mouse interrupt	d2 287, 295, 297
using DOS/4GW 28	i 287
multi-threaded applications 221, 247	Open Watcom Strip Utility 287
OS/2 2.x 247	opening more than 20 files 294
Windows NT 221	optimization
multi-threading issues	suggested reading 286
OS/2 2.x 247	what you should know 286
Windows NT 221	OS/2
	fullscreen application 239, 243
	PM-compatible application 239, 243
	Presentation Manager application 239, 243
N	OS/2 PDD 261
	OS/2 physical device drivers 261
	OS/2 PM
	API calls 258
NE format 43	non-GUI applications 257
near 139	non-GUI example 257
near pointer 139	OS/2 Presentation Manager 257
NEC 98-series switch mode setting 48	OS2.LIB 262
NETWARE_INCLUDE environment variable 267	002.212 202
NLM	
debugging 267	
header files 267	P
import libraries 267	
libraries 267	
sampler 267	
NLM support	page locking services 80
version 4.0 267	page tuning services 81
version 4.1 267	parameters
NOAUTOPROCS 150	what you need to know 283
NOCOVERSENDS 147-148	PASCAL 152, 174, 177
Novell	PASS_WORD_AS_POINTER 194
TCPIP.EXE 118	patch level 281
NT development 211	patches 281
NULL assignment detected 291	PATH environment variable 131, 135-136
debugging 291	PATH, environment variable 165
NULL pointer 284	PDD 261
NULLP 47	PENWIN.H 144
	PENWOEM.H 144
	performance 90
	Phar Lap
0	386LINK 289
	Phar Lap TNT 211
	physical device drivers 261
11 (11 ( 10 11 100 107 100 107 011 010 010	PMINFO 49, 89
object file 6, 10, 14, 122, 127, 130, 135, 214, 218, 240,	pointers
244	16-bit 139
OKI if 800 switch mode setting 48	32-bit 139
OLE.H 144	far 139
Open Watcom C/C++	

near 139	
portability	
NULL pointer 284	<b>S</b>
signed char 284	
porting	
from Microsoft C 293	segment ordering 262
from UNIX 293	segment ordering 202 segment registers
POSIX applications 233	DS 286
POSIX libraries 233	segmented executable 43
pragma 286	selector
loadds option 286	A000 201
predefined macros	B000 201
WATCOMC 285	B800 201
PRINT.H 144	B600 201 C000 201
printf 5, 9, 13, 126, 134, 217, 239, 243	C000 201 D000 201
private memory pool 91	E000 201
PRIVATXM 50, 91, 117	F000 201
problems	<del></del>
with d2 and d1 options 287	LocalPtr 201
PROCPTR 198, 203	SendDigItemMessage 147
program timer 263	SendMessage 147
protected mode 51	setjmp 144
PS/2 switch mode setting 48	SetResourceHandler 186 SetTimer 186
pushing arguments	2012
what you need to know 283	setvbuf 111
,	SetWindows Look 186
	SetWindowsHook 186
	SHELLAPI.H 144
<b>Q</b>	short 140
	signed char 284
	simulating real-mode interrupts 32
	size of DGROUP exceeds 64K 290
questions 281	_small_code_ 288
QUIET 47	spawn 26
	using DOS/4GW 26
	using Phar Lap 27
	stack overflow 292
R	static linking 225, 251
	Strategy routine 262
	STRESS.H 144
	structure alignment 211
real mode 51	stub program 43, 88
real-mode memory 24	supervisor 130, 135
using DOS/4GW 24	SWAPINC virtual memory option 53, 112-113
using Phar Lap 25	SWAPMIN virtual memory option 53, 112-113
registers	SWAPNAME virtual memory option 53, 112
calling convention 283	switch mode setting
ReleaseProc16 195	Fujitsu FMR-70 48
request packets 263	Hitachi B32 48
resource compiler 131, 135	IBM PS/55 48
RMINFO 92	NEC 98-series 48
	OKI if800 48
	PS/2 48
	switching modes
	performance 89

symbolic information 287 UDP16 ENDLIST 177 system configuration file 241 UDP16\_PTR 177 system initialization file UDP16 WORD 177 **AUTOEXEC.BAT 287** unable to find files 287 SYSTEM.INI 144 undefined references 288 \_big\_code\_ 289 cstart 288 \_fltused\_ 288 main\_ 289 \_small\_code\_ 288 WinMain 289 UNIX 284 TCPIP.EXE 118 TECHINFO 281 technical support Tenberry Software 103 termination OS/2 2.x dynamic link library 255 thread creation OS/2 2.x 247-248 variable number of arguments 284 Windows NT 221-222 variables thread example set to zero 289 OS/2 2.x 249 VCPI 50 Windows NT 223 VER.H 144 thread identifier VERBOSE 47 OS/2 2.x 248 video memory 18 Windows NT 222 using DOS/4GW 18 thread limits using Phar Lap 19 OS/2 2.x 250 virtual memory manager 53, 111 thread termination VIRTUALSIZE virtual memory option 53, 112-113 OS/2 2.x 248 Visual Basic 165 Windows NT 222 16-bit DLL 168-169 \_threadid macro 222, 248 32-bit DLL 168 threads of execution 221, 247 building examples 170 Throw 144 example 166 Version 3.0 165 timer i8523 263 VMC extension 54 TIMER.EXE 263 VMM 53, 111 TlsAlloc 227-228 TlsFree 228 TNT 211 W TOOLHELP.H 144 transfer rate memory 89 translation services 71 W386DLL.EXT 131, 135 WATCOM environment variable 131, 135-136, 223, 249, 288 \_\_WATCOM\_Prelude 267 \_\_WATCOMC\_\_ 285 WBIND 130-131, 135, 198 WBIND.EXE 130, 135 UDP16\_CDECL 177 WCL 6-7, 122-123, 127, 240-241 WCL386 10-11, 14-15, 131-132, 136, 214-215, UDP16\_CHAR 177

UDP16\_DWORD 177

218-219, 244-245

WDEBUG.386 144 WEMU387.386 144 WIN16.H 143 Win32 SDK 233 WIN386 library routines 171 WIN386.EXT 130-131, 135 WIN386.H 143 Win386LibEntry 165 windowed applications default windowing environment 125, 133 Windows binding 32-bit applications 130, 135 Windows 3.x extender 139 16xxx functions 198, 205 32-bit callback routines 198 aliases 199 AllocAlias16 199 calling 16-bit code 197 components 141 creating applications 142 floating-point 144 function pointers 198 MK\_FP16 199 MK\_FP32 199 multiple instances 145 overview 140 pointer conversion 146 pointer handling 145 pointers 139 pointers in structures 199 programming notes 143 questions 197 resources 198 special functions 205 structure 141 thunks 199 WinExec 197 Windows API functions Catch 144 Throw 144 Windows NT 211 character-mode applications 211 GUI applications 211 programming notes 211 programming overview 211 Windows NT Character-mode application 217 Windows NT Character-mode applications 217 Windows NT GUI application 213 Windows NT GUI applications 213 Windows supervisor 130, 135 WINDOWS.H 143-144, 147 \_WINDOWS\_386\_\_ 170 \_\_WINDOWS\_\_ 170

WINDOWS\_INCLUDE environment variable 165, 170 WinMain 157, 289 WORD 203 WSTUB.C 43



XMS 51