

# HP LoadRunner

Software Version: 12.00

## LoadRunner User Guide

Document Release Date: March 2014

Software Release Date: March 2014



## Legal Notices

### Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

### Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

### Copyright Notice

© Copyright 1993-2014 Hewlett-Packard Development Company, L.P.

### Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

Oracle and Java are registered trademarks of Oracle and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to: <http://h20230.www2.hp.com/selfsolve/manuals>

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to: <http://h20229.www2.hp.com/passport-registration.html>

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

## Support

Visit the HP Software Support Online web site at: <http://www.hp.com/go/hpsoftwaresupport>

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

To find more information about access levels, go to:

[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)

**HP Software Solutions Now** accesses the HPSW Solution and Integration Portal Web site. This site enables you to explore HP Product Solutions to meet your business needs, includes a full list of Integrations between HP Products, as well as a listing of ITIL Processes. The URL for this Web site is <http://h20230.www2.hp.com/sc/solutions/index.jsp>

## About this PDF Version of Online Help

This document is a PDF version of the online help. This PDF file is provided so you can easily print multiple topics from the help information or read the online help in PDF format. Because this content was originally created to be viewed as online help in a web browser, some topics may not be formatted properly. Some interactive topics may not be present in this PDF version. Those topics can be successfully printed from within the online help.

# We appreciate your feedback!

If you have comments about this document, you can [contact the documentation team by email](#). If an email client is configured on this system, click the link above and an email window opens with the following information in the subject line:

**Feedback on LoadRunner User Guide (LoadRunner 12.00)**

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to [sw-doc@hp.com](mailto:sw-doc@hp.com).

LoadRunner User Guide  
We appreciate your feedback!

# Contents

LoadRunner User Guide .....	1
We appreciate your feedback! .....	6
Contents .....	8
Welcome to the LoadRunner User Guide .....	58
LoadRunner Online Help .....	58
Additional Online Resources .....	58
What's New in LoadRunner 12.00 .....	60
VuGen Concepts .....	64
VuGen - Overview .....	64
Vuser Technology Overview .....	64
Vuser Types .....	65
Vuser Protocols .....	66
Keyboard Shortcuts .....	69
IPv6 Support .....	72
VuGen User Interface .....	75
VuGen User Interface - Overview .....	75
VuGen Layouts - Overview .....	79
Solution Explorer - Overview .....	80
Editor - Overview .....	82
Snapshot Pane - Overview .....	85
How to Work with Snapshots .....	88
How to Add a Text Check From the XML View in the Snapshot Pane .....	90
How to Create a Vuser Script - Workflow .....	91
How to Compare Scripts Side by Side .....	91
How to Create a Business Process Report .....	92
How to Modify the VuGen Layout .....	93
Options Overview .....	94
General Options .....	95
Editor Options .....	98

Scripting Options .....	103
Search and Replace Dialog Boxes .....	109
Editor .....	112
Thumbnail Explorer .....	113
Business Process Report Dialog Box .....	115
Steps Toolbox Pane .....	117
Solution Explorer Pane .....	118
Output Pane .....	124
Snapshot Pane .....	126
Bookmarks Pane .....	131
Step Navigator Pane .....	132
Errors Pane .....	133
Task Pane .....	134
Breakpoints Pane .....	135
Watch Pane .....	138
Run Time Data Pane .....	138
Call Stack Pane .....	139
Replay Summary Tab .....	140
VuGen - Troubleshooting and Limitations .....	146
Protocol Advisor - Overview .....	147
How to use the Protocol Advisor .....	148
Protocol Advisor Dialog Box .....	150
Protocol Advisor - Troubleshooting and Limitations .....	151
HP Live Network (HPLN) Integration .....	152
How to Download Content from HP Live Network (HPLN) to LoadRunner .....	152
How to Upload Content from LoadRunner to HP Live Network (HPLN) .....	154
HP Live Network Connection Dialog Box .....	157
Download from HP Live Network Dialog Box .....	158
Script Workflow .....	162
How to Create or Open a Vuser Script .....	162
Creating Vuser Scripts - Overview .....	162

How to Create and Open Vuser Scripts .....	163
Working with Application Lifecycle Management .....	163
Managing Scripts Using ALM - Overview .....	164
ALM Version Control - Overview .....	164
How to Work with Scripts in ALM Projects .....	164
How to Connect to ALM .....	165
How to Work with Version Controlled Scripts in ALM Projects .....	165
How to Save VuGen Vuser Scripts to ALM Projects .....	166
How to Compare Previous Versions of a Script .....	167
HP ALM Connection Dialog Box [VuGen] .....	167
Multiple Protocol Scripts .....	169
Script Directory Files .....	170
Create a New Script Dialog Box .....	170
How to Work with .zip Files .....	172
Vuser Script Templates .....	172
How to Create and Open Vuser Script Templates .....	173
Recording a Vuser Script .....	174
Recording - Overview .....	174
How to Record a Vuser Script .....	175
Recording Options .....	176
Citrix > Configuration Node .....	177
Citrix > Code Generation .....	177
Citrix > Login Node .....	178
Citrix > Recorder Node .....	179
COM/DCOM > Filter Node .....	180
COM/DCOM > Options Node .....	182
Correlations > Configuration .....	184
Correlations > Rules .....	186
New Rule Pane .....	187
Advanced Correlation Properties Dialog Box .....	189
Token Substitution Testpad Dialog Box .....	189

Database > Database Node .....	190
Database > Advanced Recording Options Dialog Box .....	190
Data Format Extension > Chain Configuration Node .....	191
Add Prefix/Postfix to Chain Dialog Box .....	193
Add Data Format Extension .....	194
Data Format Extension > Code Generation Node .....	195
Flex > RTMP Node .....	197
Flex > Configuration Node (Recording) .....	197
Flex > Externalizable Objects Node (Recording) .....	198
General > Code Generation .....	199
General > Protocol Node .....	200
General > Recording Node .....	200
Advanced URL Dialog Box .....	201
Advanced HTML Dialog Box .....	202
General > Script Node .....	203
GUI Properties > Web Event Configuration Node .....	205
Custom Web Event Recording Configuration Dialog Box .....	206
HTTP > Advanced Node .....	208
Headers Dialog Box .....	211
Content Type Filters Dialog Box .....	212
Non-Resources Dialog Box .....	212
Flex > Configuration Node (Recording) .....	213
Flex > Externalizable Objects Node (Recording) .....	214
.NET > Filters Node .....	215
Create a New Filter Dialog Box [.NET Protocol] .....	216
Filter Manager [.NET Protocol] .....	216
Add Reference Dialog Box [.NET Protocol] .....	219
GUI Properties > Advanced Node .....	219
.NET > Recording - Recording Node .....	221
Remote Objects Property .....	223
.NET > Shared DLLs .....	224

Mobile TruClient Properties > Mobile Device Node .....	225
Network > Port Mapping Node .....	226
Server Entry Dialog Box .....	227
Advanced Port Mapping Settings Dialog Box .....	229
RDP > Code Generation > Advanced Node .....	229
RDP > Code Generation > Agent Node .....	230
RDP > Code Generation > Basic Node .....	231
RDP > Client Startup Node .....	232
Recording Properties > Corba Options Node .....	233
Recording Properties > Correlation Options Node .....	234
Recording Properties > Log Options Node .....	234
Recording Properties > Recorder Options Node .....	235
Recording Properties > Serialization Options Node .....	236
RTE > Configuration Node .....	237
RTE > RTE Node .....	238
SAPGUI > Auto Logon Node .....	239
SAPGUI > Code Generation Node .....	239
SAPGUI > General Node .....	240
Silverlight > Services Node .....	240
Add / Edit Services Dialog Box .....	241
Connection Settings Dialog Box .....	242
Protocol and Security Scenario Data Dialog Box .....	242
Traffic Analysis > Traffic Filter .....	243
WinSock Node .....	244
Recording Options - Miscellaneous Topics .....	246
Protocol Compatibility Table .....	246
Port Mapping Overview .....	249
Port Mapping Auto Detection .....	250
EUC-Encoding (Japanese Windows only) .....	251
Script Generation Preference Overview .....	251
Script Language Options .....	252

Recording Levels - Overview .....	252
Serialization Overview .....	253
Tips for Working with Event Listening and Recording .....	254
Example of Click & Script Out of Context Recording .....	254
Vuser Script Sections .....	255
Providing Authentication Information .....	258
Recording via a Proxy- Overview .....	260
How to Record a Script via a Proxy .....	261
How to Import Actions to a Script .....	265
How to Regenerate a Vuser Script .....	266
Start Recording Dialog Box .....	266
Floating Recording Toolbar .....	269
Files Generated During Recording .....	271
Troubleshooting and Limitations - Recording .....	273
Correlation Studio .....	274
Correlation Overview .....	274
Correlation Tab [Design Studio] Overview .....	275
Determining Which Values to Correlate .....	277
Modifying Saved Parameters .....	278
Correlation vs. Parameterization .....	278
Wdiff Correlation Utility .....	278
Correlating Java Scripts .....	278
How to Correlate Scripts Using Design Studio .....	280
How To Manually Correlate Scripts .....	282
How to Correlate Scripts From a Snapshot .....	282
Correlating Winsock Scripts .....	283
How to Correlate Scripts - Winsock (Manually) .....	284
How to Correlate Scripts - Web (Manually) .....	286
How to Correlate Scripts - Siebel Protocol .....	287
How to Correlate Scripts - Oracle NCA .....	292
How to Correlate Scripts - Microsoft .NET .....	294

How to Correlate Scripts - Java Scripts - Serialization .....	296
How to Correlate Scripts - Java .....	299
How to Correlate Scripts - XPath Correlation in Flex Vuser Scripts .....	301
How to Correlate Scripts - COM Protocol .....	302
How to Search for Values that Need Correlation .....	302
How to Modify Correlation Definitions .....	303
How to Exclude Content Based on Content-Type .....	307
How to Exclude Strings from the Correlation Scan .....	308
Correlation Functions - Database Vuser Scripts .....	309
Correlation Functions - Java Vuser Scripts .....	309
Web_reg_save_param function details .....	310
Correlation Functions - C Vuser Scripts .....	311
Design Studio [Correlation Tab] Dialog Box .....	312
Replaying a Vuser Script .....	316
Replaying - Overview .....	316
How to Replay a Vuser Script .....	316
Run-Time Settings .....	317
Run-Time Settings - Miscellaneous Topics .....	317
Content Checking Overview .....	317
Copying, Importing, and Exporting Run-Time Settings .....	318
Multithreading .....	320
Protocol Compatibility Table .....	320
Browser > Browser Emulation Node .....	325
Citrix > Configuration Node .....	327
Citrix > Synchronization Node .....	328
COM/DCOM > Filter Node .....	329
COM/DCOM > Options Node .....	331
Data Format Extension > Configuration Node .....	332
Flex > Configuration Node (Run-Time Settings) .....	332
Flex > RTMP Node .....	333
Flex > Externalizable Node (Run-Time Settings) .....	334

General > Additional Attributes Node .....	335
General > Log Node .....	335
General > Log Node (AjaxTruClient) .....	336
General > Advanced Settings (TruClient) .....	338
Load > Browser Settings Node (Ajax TruClient) .....	338
Load > Other Settings (TruClient) .....	342
General > Replay Node .....	343
General > Miscellaneous Node .....	348
General > Pacing Node .....	349
General > Run Logic Node .....	350
General > Think Time Node .....	350
Internet Protocol > ContentCheck Node .....	351
Internet Protocol > Download Filters Node .....	352
Internet Protocol > Preferences Node .....	353
Advanced Options Dialog Box .....	354
Internet Protocol > Proxy Node .....	363
Java Environment Settings > Java Classpath Node .....	364
Java Environment Settings > Java VM Node .....	365
JMS > Advanced Node .....	366
MMS > Server and Protocol Node .....	368
Mobile TruClient Properties > Mobile Device Node .....	368
.NET > .NET Environment Node .....	369
.NET > Shared DLLs .....	370
Network > Speed Simulation Node .....	371
Oracle NCA > Client Emulation Node .....	371
RDP > Advanced Node .....	372
RDP > Configuration Node .....	373
RDP > RDP Agent Node .....	374
RDP > Synchronization Node .....	375
RTE > RTE Node .....	376
SAPGUI > General Node .....	377

Silverlight > Services Node .....	378
WAP > Gateway Node .....	379
WAP > Radius Node .....	381
Bookmarks Overview .....	382
How to Run a Vuser Script from a Command Prompt .....	382
How to Run a Vuser Script from a Linux Command Line .....	383
How to Use Bookmarks .....	385
Files Generated During Replay .....	386
Debugging Vuser Scripts .....	387
Debugging - Overview .....	388
Error Handling .....	390
Additional Debugging Information .....	391
Working with Breakpoints .....	392
Watching Expressions and Variables .....	392
Debugging Web Vuser Scripts .....	393
How to Debug Scripts with Breakpoints .....	394
Enhancing a Script for Load Testing .....	395
Enhancing a Script for Load Testing - Overview .....	395
Transaction Overview .....	397
How to Insert Transactions .....	398
How to Display Transactions .....	399
Rendezvous Points .....	400
Adding VuGen Functions - Overview .....	400
General Vuser Functions .....	402
Protocol-Specific Vuser Functions .....	402
Encrypting Text .....	403
Password Encoding .....	403
Encrypting Text .....	403
How to Encrypt/Decrypt Text .....	404
How to Encode a Password .....	404
Password Encoder Dialog Box .....	404

How to Create a Controller Scenario from VuGen .....	405
How to Insert Steps into a Script .....	406
Create Controller Scenario Dialog Box .....	406
Parameters .....	408
Parameterizing - Overview .....	408
Parameter Types .....	410
How to Create a Parameter .....	412
Data Assignment Methods for File/Table/XML Parameters .....	413
Data Assignment and Update Methods for File/Table/ XML Parameters .....	414
Vuser Behavior in the Controller (LoadRunner Only) .....	415
How to Work with Existing Parameters .....	416
XML Parameters .....	416
How to Create an XML Parameter from a Web Service Call .....	417
How to Create XML Parameters - Standard Method .....	418
How to Define XML Value Sets .....	419
How to Set an Assignment Method .....	422
How to Modify XML Parameter Properties .....	423
How to Set AUT Environment Parameters .....	424
How to Import Parameter Data from a Database .....	424
Select or Create Parameter Dialog Box .....	425
Parameter Properties Dialog Box .....	426
Parameter Simulation Dialog Box .....	435
Parameter List Dialog Box .....	439
Database Query Wizard .....	440
Create Parameter Dialog Box (Winsock) .....	441
Parameter Original Value Dialog Box .....	441
Parameters - Troubleshooting and Limitations .....	442
Async Studio .....	442
Synchronous and Asynchronous Concepts .....	443
Types of Asynchronous Communication .....	443
LoadRunner Support for Asynchronous Communication - Overview .....	446

How to Create an Asynchronous Vuser Script .....	448
Asynchronous Communication API .....	450
How Asynchronous Functions Differ from Synchronous Functions .....	451
How VuGen Modifies a Vuser Script for Asynchronous Communication .....	451
Defining the Start of an Asynchronous Conversation .....	454
Defining the End of an Asynchronous Conversation .....	456
Using Asynchronous Request Thresholds .....	457
Fine-Tuning the End of an Asynchronous Conversation .....	458
Correlating Asynchronous Vuser Scripts .....	459
Implementing Callbacks .....	459
Modifying Callbacks .....	462
Parsing URLs .....	466
Async Rules - Overview .....	468
Adding Async Rules .....	469
Async Tab [Design Studio] .....	471
Asynchronous Options Dialog Box .....	473
Asynchronous Example - Poll .....	474
Asynchronous Example - Push .....	476
Asynchronous Example - Long-Poll .....	477
Viewing Replay Results .....	479
Viewing Replay Results - Overview .....	480
Customizing the Test Results Display .....	480
Connecting to Application Lifecycle Management from the Test Results Window .....	481
How to Send Custom Information to the Report .....	481
How to Configure the Appearance of the Test Results Window .....	481
How to Open the Test Results of a Specific Run .....	481
How to Find Steps in the Test Results .....	482
Test Results Window .....	482
Filters Dialog Box .....	484
Print Dialog Box .....	485
Print Preview Dialog Box .....	486

Export to HTML File Dialog Box .....	487
<b>Protocols .....</b>	<b>489</b>
Protocol Support for Async, IPv6, and 64-bit Recording .....	489
Ajax - Click & Script Protocol .....	490
Ajax (Click & Script) Protocol Overview .....	490
Ajax (Click & Script) Supported Frameworks .....	491
Ajax (Click & Script) Example Script .....	491
Ajax (Click & Script) Recording Tips .....	492
Ajax (Click & Script) - Replay Tips .....	493
Ajax (Click & Script) Miscellaneous Tips .....	494
Click & Script Troubleshooting and Limitations .....	495
TruClient Protocol .....	499
What is TruClient? .....	499
TruClient Step Structure .....	502
Understanding Step Events .....	506
How to Synchronize TruClient Scripts Steps .....	508
Developing TruClient Scripts .....	511
How to Develop TruClient Scripts .....	511
How to Calculate the Number of Load Generators Required for TruClient Scripts .....	513
TruClient - Debugging a TruClient Script .....	515
TruClient Alternative Steps .....	515
TruClient Script Levels .....	515
TruClient Snapshots .....	517
How to Debug TruClient Scripts .....	517
Additional Script Debugging Tips .....	519
How to Resolve Object Identification Issues .....	519
Troubleshooting Object Identification Issues .....	525
Troubleshooting TruClient Scripts .....	527
TruClient - Enhancing a TruClient Script .....	531
TruClient Event Handlers .....	531
TruClient Functions and Function Libraries .....	533

Working With JavaScript in TruClient Scripts .....	533
JavaScript Support .....	533
How Can I Learn More about JavaScript .....	533
Using Regular Expressions .....	534
How to Enhance TruClient Scripts .....	534
How To Use The Events Handler .....	536
How to Insert and Modify Loops .....	538
How to Insert Custom JavaScript and C Code into TruClient Scripts .....	539
How to Use VTS in TruClient .....	539
How To Create and Use Function and Libraries .....	542
How to Display Client Side Breakdown Data for TruClient Scripts .....	544
TruClient Events Handler Editor Dialog Box .....	544
TruClient Client Side Breakdown Data .....	547
Create New Function Dialog Box .....	549
Transaction Editor Dialog Box (TruClient) .....	550
The TruClient Sidebar .....	553
TruClient Home Tab .....	553
TruClient Edit Tab .....	556
Window Tab .....	558
TruClient Toolbox .....	558
Browsers in TruClient .....	560
General Browser Settings (TruClient) .....	560
Private Browsing (TruClient) .....	560
TruClient Browser for IE .....	561
TruClient General Settings Dialog Box .....	562
TruClient - Troubleshooting and Limitations (General) .....	564
Troubleshooting Communication between VuGen and TruClient .....	565
Word Verification Function in the Business Process .....	565
Protocol Limitations .....	566
Converting a TruClient Script to a Web HTTP/HTML Script .....	567
LR Function Reference .....	568

TruClient Functions .....	.568
TruClient VTS Functions .....	.571
TruClient Properties .....	.578
TruClient Step Arguments .....	.579
Citrix Protocol .....	.584
Citrix Protocol - Overview .....	.584
Citrix Recording Tips .....	.584
Citrix Replaying Tips .....	.586
Citrix Synchronization .....	.587
Citrix - Automatic Synchronization .....	.587
Citrix Alternate Synchronization .....	.588
Agent for Citrix Presentation Server - Overview .....	.590
Troubleshooting XenApp 5.0 .....	.593
How to Configure the Citrix Client and Server .....	.593
How to Synchronize Citrix Scripts Manually .....	.594
How to Install and Uninstall the Citrix Agent .....	.595
Citrix Functions .....	.595
Citrix - Understanding ICA Files .....	.596
Failed Bitmap Synchronization Dialog Box .....	.597
Citrix - Troubleshooting and Limitations .....	.597
Click & Script Protocols .....	.601
Click & Script Protocols - Overview .....	.602
Click & Script Recording Tips .....	.603
Click & Script - Replay Tips .....	.604
Click & Script Miscellaneous Tips .....	.606
Click & Script Enhancements .....	.606
Click & Script API Notes .....	.609
Ordinals .....	.609
Empty Strings .....	.610
Click & Script Troubleshooting and Limitations .....	.610
COM Protocol .....	.614

COM Protocol Overview .....	614
COM Technology Overview .....	615
COM Vuser Script Structure .....	616
COM Sample Vuser Scripts .....	617
Selecting COM Objects to Record .....	621
Database Protocols .....	622
Database Protocols Overview .....	622
VuGen Database Recording Technology .....	623
Database Grids .....	623
Flex (RTMP/AMF) Protocol .....	625
Flex Overview .....	625
Recording Flex Scripts .....	627
AMF .....	628
RTMP Functions .....	629
RTMP Tunneled Functions .....	630
RTMP/RTMPT Streaming .....	630
RTMP Tunneled .....	638
How to Record a Flex Script .....	639
Setting the Flex Recording Mode .....	640
Example .....	640
Code Generation in the Flex Protocol .....	641
Externalizable Objects in Flex Scripts .....	642
Flex Correlations .....	643
Flex Snapshots .....	644
How to Serialize Flex Scripts .....	645
How to Query an XML Tree .....	646
Flex - Troubleshooting and Limitations .....	648
GraniteDS (Data Services) .....	649
Java Protocols .....	650
Java Protocol Recording Overview .....	650
Java Vuser Script Overview .....	651

RMI over IIOP Overview .....	651
Corba Recording Options .....	652
CORBA Application Vendor Classes .....	652
Recording RMI .....	652
Recording a Jacada Vuser .....	652
Working with CORBA .....	653
Working with RMI .....	654
Working with Jacada .....	655
Java Custom Filters - Overview .....	656
Java Custom Filters - Determining which Elements to Include .....	657
How to Record a Java Vuser Script .....	657
How to Record Java Scripts Using Windows XP and 2000 Server .....	658
How to Run a Script as Part of a Package .....	659
How to Manually Insert Java Methods .....	659
How to Manually Configure Script Generation Settings .....	661
How to Create a Custom Java Filter .....	663
Hook File Structure .....	664
Java Icon Reference List .....	666
Java Vuser Protocol - Manually Programming Scripts .....	667
Manually Programming Java Scripts - Overview .....	667
Java Protocol Programming Tips .....	667
Running Java Vuser Scripts .....	669
Opening Java Vuser Scripts in Eclipse .....	670
Compiling and Running a Script as Part of a Package .....	670
How to Manually Create a Java Script .....	671
How to Enhance a Java Script .....	673
Troubleshooting and Limitations - Java Protocol .....	677
Java over HTTP Protocol .....	677
Java over HTTP Protocol Overview .....	677
Viewing Responses and Requests in XML Format .....	677
How to Record with Java over HTTP .....	678

How to Debug Java over HTTP scripts .....	679
How to Insert Parameters into Java over HTTP Scripts .....	680
Java over HTTP - Troubleshooting and Limitations .....	680
LDAP Protocol .....	681
LDAP Protocol Overview .....	682
LDAP Protocol Example Script .....	682
Defining Distinguished Name Entries .....	683
LDAP Connection Options .....	684
Troubleshooting and Limitations - LDAP .....	685
Mailing Service Protocols .....	685
Mailing Service Protocols Overview .....	685
IMAP Protocol Overview .....	686
MAPI Protocol Overview .....	686
POP3 Protocol Overview .....	687
SMTP Protocol Overview .....	687
Mobile Protocols .....	688
Mobile Protocols Overview .....	688
Protocol Options for Mobile .....	688
How to Select a Recording Method for Mobile Applications .....	689
Network Speed Simulation .....	691
Network > Speed Simulation Node .....	692
Mobile Application - HTTP/HTML .....	693
Recording Methods .....	693
Recording Traffic into a Capture (Sniffer) File .....	694
Record Traffic with VuGen's Mobile Sniffer Agent .....	695
Capture Traffic With an External SnifferTool .....	697
Analyzing Traffic .....	698
Recording with Emulation .....	699
How to Create a Script by Analyzing Traffic .....	704
How to Record and Analyze a Script for Mobile Applications .....	707
How to Record with the Mobile Recorder .....	708

Recording Wizard .....	709
Recording Method Dialog Box .....	710
Analyze Traffic Dialog Box .....	710
Configure and Record Dialog Box .....	711
Record Emulation Dialog Box .....	712
Proxy Recording Dialog Box .....	712
LoadRunner Mobile Recording Application User Interface .....	713
Mobile TruClient .....	715
Mobile TruClient Protocol .....	715
How to Record a Script with Mobile TruClient .....	715
How to Add, Remove, and Import Mobile Device Settings for Mobile TruClient .....	716
Mobile TruClient Device Manager Dialog Box .....	716
SAP Mobile Platform .....	717
How to create an SMP (SAP Mobile Platform) script .....	717
.NET Protocol .....	718
.NET Protocol Overview .....	718
Considerations for Working with the .NET Protocol .....	718
Viewing Data Sets and Grids .....	719
Recording WCF Duplex Communication .....	720
Replacement of the Callback in the Script .....	723
Asynchronous Calls .....	724
Recording Dual HTTP Bindings .....	725
Connection Pooling .....	725
Debugging .NET Vuser Scripts .....	726
.NET Filters Overview .....	727
.NET Filters - Advanced .....	728
Guidelines for Setting .NET Filters .....	729
How to Configure Application Security and Permissions .....	732
.NET - Troubleshooting and Limitations .....	733
Oracle NCA Protocol .....	734
Oracle NCA Protocol Overview .....	734

Oracle NCA Protocol Example Scripts .....	735
Oracle NCA Record and Replay Tips .....	736
Pragma Mode .....	736
How to Enable the Recording of Objects by Name .....	738
How to Launch Oracle Applications via the Personal Home Page .....	740
Oracle NCA - Troubleshooting and Limitations .....	740
RDP Protocol .....	742
RDP Protocol - Overview .....	743
RDP Recording Tips .....	743
Working with Clipboard Data (RDP Protocol) .....	745
Correlating Clipboard Parameters .....	747
RDP Snapshots - Overview .....	747
Image Synchronization Overview .....	748
Image Synchronization Tips (RDP Protocol) .....	749
Image Synchronization - Shifted Coordinates (RDP Protocol) .....	750
Setting Security Levels in RDP Vuser Scripts .....	750
RDP Agent (Agent for Microsoft Terminal Server) Overview .....	753
How to Install / Uninstall the RDP Agent .....	755
How to Add Image Synchronization Points to a Script .....	756
Failed Image Synchronization Dialog Box (RDP Protocol) .....	756
RDP - Troubleshooting and Limitations .....	758
RTE Protocol .....	759
RTE Protocol Overview .....	759
Working with Ericom Terminal Emulation .....	760
SSL and SSH Support for Ericom .....	761
Typing Input into a Terminal Emulator .....	762
Setting the Timeout Value for TE_type .....	762
Allowing a Vuser to Type Ahead .....	763
Generating Unique Device Names .....	763
Setting the Field Demarcation Characters .....	764
Reading Text from the Terminal Screen .....	765

RTE Synchronization Overview .....	766
Synchronizing Block-Mode (IBM) Terminals .....	767
Synchronizing Character-Mode (VT) Terminals .....	769
How to Map Terminal Keys to PC Keyboard Keys .....	772
How to Record RTE Vuser Scripts .....	773
How to Implement Continue on Error .....	775
RTE - Terminal Emulation - Troubleshooting and Limitations .....	776
SAP Protocols .....	776
Selecting a SAP Protocol Type .....	776
SAP GUI Protocol .....	776
SAP Web Protocol .....	779
SAP (Click & Script) Protocol .....	780
Replaying SAP GUI Optional Windows .....	781
How to Configure the SAP Environment .....	782
How to Record SAP GUI Scripts .....	787
How to Replay SAP GUI Scripts .....	789
How to Run SAP GUI Scripts in a Scenario .....	789
How to Enhance SAP GUI Scripts .....	790
Additional SAP Resources .....	795
SAP GUI, SAP Web, and SAP (Click & Script) - Troubleshooting and Limitations .....	795
Siebel Web Protocol .....	797
Siebel Web Protocol Overview .....	797
Siebel Web Recording Options and Run-Time Settings .....	797
How to Record Transaction Breakdown Information .....	798
Siebel Web - Troubleshooting and Limitations .....	799
Silverlight Protocol .....	801
Silverlight Protocol - Overview .....	801
How to Import WSDL Files .....	801
Silverlight - Troubleshooting and Limitations .....	802
Web (HTTP/HTML) Protocol .....	803
Web (HTTP/HTML) Protocol - Overview .....	803

Using the LoadRunner JavaScript Engine .....	806
JavaScript Engine: XMLHttpRequest Example .....	811
How to Convert a Web (HTTP/HTML) Vuser Script into a Java Vuser Script .....	812
How to create a script for a REST API .....	813
Examples .....	814
How to record the SPDY protocol .....	815
Applications that Use Smooth Streaming .....	815
Converting a TruClient Script to a Web HTTP/HTML Script .....	817
Troubleshooting and Limitations - Web (HTTP/HTML) Protocol .....	818
Web Protocols (Generic) .....	818
Web Protocols - Overview .....	818
Web Vuser Technology .....	819
Web Vuser Types .....	820
Text and Image Verification (Web Vuser Scripts) - Overview .....	820
Understanding Web Text Check Functions .....	821
How to Add Text Checks and Image Checks (Web Vuser Protocols) .....	822
Web Snapshots - Overview .....	823
Browser Emulation - Overview .....	825
How to Perform Load Testing with nCipher HSM .....	827
Working with Cache Data .....	828
How to Insert Caching Functions .....	830
Data Format Extensions (DFEs) - Overview .....	831
How to Implement Data Format Extension (DFE) Support .....	834
How to Define a Chain of DFEs .....	834
How to Enable DFE Support .....	835
How to Configure DFE Support .....	836
How to Apply DFE Chains to Sections of the HTTP Message .....	837
How DFEs Modify a Vuser Script .....	838
Data Format Extension List .....	839
Applying DFEs to a String .....	840
Google Web Toolkit - Data Format Extension (GWT-DFE) - Overview .....	841

Implementing GWT-DFE Support .....	845
Troubleshooting - Data Format Extension (DFE) .....	847
Web Services .....	847
Web Services - Adding Script Content .....	847
Web Service Testing Overview .....	847
Adding Web Service Script Content - Overview .....	848
Script Integration .....	849
Web Service Call Attachments .....	850
Special Argument Types .....	850
Server Traffic Scripts Overview .....	853
Capture Files .....	854
Filtering Traffic .....	855
Data on Secure Servers .....	856
How to Add Content .....	856
How to Assign Values to XML Elements .....	858
How to Generate a Test Automatically .....	859
How to Create a Script by Analyzing Traffic .....	860
How to Create Capture Files Using lrtcpdump .....	861
Specify Services Screen .....	862
Specify Application to Record Dialog Box .....	863
Import SOAP Dialog Box .....	864
New Web Service Call Dialog Box .....	865
Add Input Attachment Dialog Box .....	872
Add Array Elements Dialog Box .....	873
Process Base64 Data - Simple Data Dialog Box .....	873
Process Base64 Data - Complex Data Dialog Box .....	874
Aspects List .....	875
Specify Services Screen .....	876
Specify Traffic Information Screen .....	877
SSL Configuration Dialog Box .....	877
Web Services - Preparing Scripts for Replay .....	878

Preparing for Replay Overview .....	878
Testing Web Service Transport Layers Overview .....	879
Sending Messages over HTTP/HTTPS .....	879
JMS Transport Overview .....	879
JMS Script Functions .....	880
JMS Message Structure .....	881
Asynchronous Messages Overview .....	881
Sending Asynchronous Calls with HTTP/HTTPS .....	881
WS-Addressing .....	882
Database Integration Overview .....	883
Connecting to a Database .....	884
Using Data Retrieved from SQL Queries .....	884
Validating Database Values after a Web Service Call .....	886
Checking Returned Values Through a Database .....	887
Performing Actions on Datasets .....	889
Customizing Overview .....	889
User Handlers .....	889
Custom Configuration Files .....	891
User Handler Examples .....	892
How to Prepare Scripts for Replay .....	894
How to Send Messages over JMS .....	895
How to Send Messages over HTTP/S .....	896
How to Define a Testing Method .....	898
How to Add a Database Connection .....	899
How to Create a User Handler .....	900
How to Customize Configuration Files .....	903
Web Services Snapshots - Overview .....	903
Database Connection Dialog Box .....	906
Connection String Generator Dialog Box .....	906
Web Services - Managing Services .....	907
Managing Services Overview .....	907

Importing Services .....	910
Comparison Reports .....	910
Web Reference Analyzer .....	911
How to Add and Manage Services .....	912
How to Analyze WSDL Dependencies .....	913
Manage Services Dialog Box .....	913
Connection Settings Dialog Box .....	916
Import Service Dialog Box .....	917
Search for Service in UDDI Dialog Box .....	917
XML/WSDL Comparison Dialog Box .....	918
WSDL Reference Analyzer Dialog Box .....	919
Web Services - Security .....	919
Setting Security Overview .....	919
Security Tokens and Encryption .....	920
SAML Security Options .....	923
Security Scenarios Overview .....	924
Choosing a Security Model .....	924
Private, Imported, and Shared Scenarios .....	925
Scenario Categories .....	925
WCF Scenario Settings .....	927
The WsHttpBinding Scenario .....	928
The Federation Scenario .....	929
The Custom Binding Scenarios .....	930
Advanced Scenario Setting .....	931
WCF Extensibility .....	936
Preparing Security Scenarios for Running .....	937
Parameterizing Security Elements .....	937
Protecting Custom Headers .....	937
Emulating Users with Iterations .....	938
How to Add Security to a Web Service Script .....	939
How to Add SAML Security .....	940

How to Create and Manage Security Scenarios .....	940
How to Parameterize Security Elements .....	942
Set Security Properties Dialog Box .....	943
Security Scenario Editor Dialog Box .....	948
Select Certificate Dialog Box .....	948
Web Services Security Examples .....	950
Troubleshooting and Limitations - Web Services .....	952
Troubleshooting and Limitations - Web Services .....	953
Windows Sockets Protocol .....	954
Recording Windows Sockets - Overview .....	954
Translation Tables .....	954
Windows Sockets Data .....	955
Windows Sockets Snapshots - Overview .....	956
Data Navigation Tools .....	958
Buffer Data Editing .....	958
How to Record a Windows Sockets Script .....	959
How to View and Modify Windows Sockets Buffers .....	960
Data Buffers .....	963
Go To Offset Dialog Box .....	964
MMS (Multimedia Messaging Service) Protocol Overview .....	965
How to Run an MMS Scenario in the Controller .....	965
Advanced Topics .....	967
Manually Programming a Script using the VuGen Editor .....	967
Manually Programming Scripts - Overview .....	967
C Vuser Scripts .....	967
Java Vusers .....	968
.NET Vusers .....	969
Creating Scripts in External IDEs .....	969
Creating Vuser Scripts or LoadRunner Tests in Visual Studio or Eclipse .....	969
How to Create a Vuser Script in Visual Studio .....	970
How to Create a Vuser Script in Eclipse .....	971

How to Develop a Unit Test Using Visual Studio (NUnit test) .....	972
How to Develop a Unit Test Using Eclipse (JUnit or Selenium test) .....	973
Using DLLs and Customizing VuGen .....	974
Calling Functions from External DLLs .....	974
How to Load a DLL Locally .....	975
How to Load a DLL Globally .....	976
Recording OLE Servers .....	976
Using CmdLine .....	977
CmdLine Environment Variables .....	978
How to Create a New Vuser Type .....	978
VuGen File and Library Locations .....	981
Storing Run-Time Settings in External Files .....	982
Creating and Running Scripts in Linux .....	982
Creating and Running Scripts in Linux - Overview .....	982
Programming Vuser Actions .....	983
How to Create a Template .....	984
How to Configure Run-Time Settings Manually .....	984
How to Define Transaction and Insert Rendezvous Points Manually .....	987
How to Compile Scripts Manually on Linux .....	987
Programming with the XML API .....	988
Programming with the XML API - Overview .....	988
Using XML Functions .....	988
Specifying XML Function Parameters .....	991
XML Attributes .....	992
Structuring XML Scripts .....	992
Enhancing a Recorded Session with XML .....	993
How to Use Result Parameters .....	996
Troubleshooting and Limitations - Programming .....	998
Non-English Language Support .....	999
Non-English Language Support - Overview .....	999
Page Request Header Language .....	1000

How to Convert Encoding Format of a String .....	1000
How to Convert Encoding Format of Parameter Files .....	1001
How to Record Web Pages with Foreign Languages .....	1002
Foreign Languages - Troubleshooting and Limitations .....	1003
Additional Components .....	1006
Third Party Components .....	1009
Installing the Citrix Server Agent .....	1009
Installing VTS .....	1010
Installing the Microsoft Terminal Server Agent .....	1011
Troubleshooting and Limitations - Additional Components .....	1011
Controller .....	1013
Understanding LoadRunner .....	1013
LoadRunner Controller Overview .....	1013
Scripts and Test Types .....	1013
Controller Workflow .....	1014
Controller Technology .....	1015
Controller Window .....	1016
HP LoadRunner Agents .....	1018
Load Testing Overview .....	1019
The HP LoadRunner Solution .....	1020
HP LoadRunner Terminology .....	1020
The HP LoadRunner Testing Process .....	1021
License Utility .....	1022
LoadRunner License Utility .....	1022
LoadRunner License Utility - New License .....	1026
How to Install a New License .....	1029
Additional Information About VUD Licenses .....	1029
Designing Load Test Scenarios .....	1030
Planning Load Test Scenarios .....	1030
Load Test Planning Overview .....	1030
Load Testing Objectives .....	1031

How to Plan a Load Test .....	1033
How to Analyze the Application .....	1033
How to Define the Load Test Objectives .....	1036
How to Plan the LoadRunner Implementation .....	1037
Designing Scenarios .....	1040
Manual Scenarios .....	1040
Changing Scenario Modes .....	1040
Goals Types for Goal-Oriented Scenarios .....	1041
How to Design a Goal-Oriented Scenario .....	1043
How to Design a Manual Scenario .....	1045
How to Change the Scenario Mode (Manual Scenario) .....	1047
How to View/Modify Scripts in the Scenario .....	1047
Relative Paths for Scripts .....	1050
Vuser Statuses .....	1050
Add Group Dialog Box .....	1051
Add Script Dialog Box .....	1052
Add Vusers Dialog Box .....	1053
Design Tab .....	1054
Edit Scenario Goal Dialog Box .....	1056
Group Information Dialog Box .....	1058
Multiple Run-Time Settings Mode Dialog Box .....	1060
New Scenario Dialog Box .....	1061
Scenario Goal Pane .....	1063
Scenario Groups/Scripts Pane - Manual Scenarios .....	1064
Scenario Scripts Pane - Goal-Oriented Scenarios .....	1067
Scenario Start Time Dialog Box .....	1069
Script Information Dialog Box .....	1070
Vuser Information Dialog Box .....	1071
Vusers Dialog Box .....	1072
Load Generators .....	1074
Load Generators - Overview .....	1074

Adding a Cloud-Based Load Generator - Overview .....	1076
How to Add a Load Generator to a Scenario .....	1077
Managing Cloud Accounts - Overview .....	1079
How to Manage Cloud Accounts .....	1081
Manage Cloud Accounts Dialog Box .....	1081
How to Modify Load Generator Settings .....	1083
Load Balancing .....	1083
Setting up a Load Generator Environment .....	1084
How to Connect/Disconnect a Load Generator .....	1084
How to Connect to a Linux Load Generator Without Using RSH .....	1084
To stop the agent daemon: .....	1085
Linux Environment Variables .....	1085
Add New Load Generator/Load Generator Information Dialog Box .....	1085
Create Cloud Load Generator Dialog Box .....	1088
Use Cloud Load Generator Dialog Box .....	1090
Load Generator Configuration > Connection Log Tab .....	1091
Load Generator Configuration > Run-Time File Storage Tab .....	1092
Load Generator Configuration > Run-Time Quota Tab .....	1093
Load Generator Configuration > Connections Tab .....	1093
Load Generator Configuration > Status Tab .....	1094
Load Generator Configuration > Terminal Services Tab .....	1094
Load Generator Configuration > Linux Environment Tab .....	1096
Load Generator Configuration > Vuser Limits Tab .....	1098
Load Generator Configuration > Vuser Status Tab .....	1099
Load Generator Configuration > Network Virtualization Tab .....	1100
Load Generators Dialog Box .....	1101
Network Profile Manager Dialog Box .....	1104
Network and Security Manager .....	1105
Network and Security Manager - Command Line Tool .....	1108
Common Examples .....	1113
Set the agent proxy and port, and the MI Listener over a firewall .....	1113

Read parameters from a file .....	1113
Remote updates .....	1113
Remote updates - multiple .....	1114
Remote updates - multiple from file .....	1114
Restarting the agent .....	1114
SSL Utility .....	1114
Scheduling Manual Scenarios .....	1116
Scheduling Manual Scenarios Overview .....	1116
Scheduling by Scenario or Group .....	1116
Schedule Run Modes .....	1117
How to Define a Schedule for the Scenario - Workflow .....	1118
How to Add Actions to the Scenario Schedule .....	1121
How to Edit Schedule Actions .....	1124
Schedule Actions .....	1125
Add Action Dialog Box .....	1127
Edit Action Dialog Box .....	1128
Scenario Schedule Pane .....	1129
Service Level Agreements .....	1129
Service Level Agreements Overview .....	1130
Tracking Period .....	1130
How to Define Service Level Agreements .....	1131
How to Define Service Level Agreements - Use-Case Scenario .....	1132
Advanced Options Dialog Box .....	1134
Goal Details Dialog Box .....	1135
Service Level Agreement Pane .....	1135
Service Level Agreement Wizard .....	1136
Select a Measurement Page .....	1137
Select Transactions Page .....	1138
Set Load Criteria Page .....	1139
Set Percentile Threshold Values Page .....	1140
Set Threshold Values Page (Goal Per Time Interval) .....	1141

Set Threshold Values Page (Goal Per Whole Run) .....	1142
Multiple IP Addresses .....	1142
Multiple IP Addresses Overview .....	1142
How to Add IP Addresses to a Load Generator .....	1143
IP Wizard .....	1144
Configuring Terminal Services Settings .....	1146
Terminal Services Overview .....	1146
About Terminal Services .....	1146
How to Use the Terminal Services Manager .....	1147
How to Configure Terminal Sessions Over a Firewall .....	1148
Configuring Network Virtualization Settings .....	1149
Network Virtualization Overview .....	1149
Virtual Locations Overview .....	1151
Excluding Machines from Network Virtualization .....	1151
How to Run a Scenario with Network Virtualization .....	1152
Network Virtualization Settings Dialog Box .....	1155
Running Load Test Scenarios .....	1156
Online Monitor Graphs .....	1156
Online Monitor Graphs Overview .....	1157
About Online Monitor Graphs .....	1157
Viewing Monitor Data Offline .....	1157
How to Display Online Monitor Graphs .....	1157
How to Customize Online Graph and Measurement Settings .....	1158
How to Manage Online Graphs .....	1160
Graph Configuration Dialog Box .....	1161
Measurement Configuration Dialog Box .....	1163
Open a New Graph Dialog Box .....	1165
Overlay Graphs Dialog Box .....	1165
Available Graphs Tree .....	1166
Configuring Scenario Options .....	1169
Configuring Scenario Options Overview .....	1169

Expert Mode .....	1170
Run-Time File Storage Locations .....	1170
Path Translation .....	1171
How to Configure Scenario Options .....	1172
Path Translation Table .....	1173
Options Dialog Box .....	1175
Options > Debug Information Tab .....	1176
Options > Execution Tab .....	1177
Options > General Tab .....	1178
Options > Monitors Tab .....	1178
Options > Output Tab .....	1180
Options > Path Translation Tab .....	1181
Options > Run-Time File Storage Tab .....	1182
Options > Run-Time Settings Tab .....	1182
Options > Timeout Tab .....	1183
Before Running Your Scenario .....	1185
How to Prepare a Scenario to Run .....	1185
Set Results Directory Dialog Box .....	1188
Summary Information Dialog Box .....	1189
Running Scenarios .....	1190
Running Scenarios Overview .....	1190
Before run .....	1190
Start of run .....	1190
During run .....	1190
End of run .....	1191
How to Run a Scenario .....	1191
Initialize, Run, or Stop Vuser Groups - Use-Case Scenario .....	1193
Control Vusers During a Scenario Run - Use-Case Scenario .....	1194
Run/Stop Individual Vusers, or Add New Vusers - Use-Case Scenario .....	1196
Initialize/Run Additional Vusers or Stop Running Vusers - Use-Case Scenario ..	1199
Execution Notes Dialog Box .....	1204

Output Window .....	1205
Filtered Tab .....	1205
Summary Tab .....	1207
Run Tab .....	1209
Run/Stop Vusers Dialog Box .....	1210
Scenario Groups Pane .....	1213
Scenario Status Pane .....	1215
Transactions Dialog Box .....	1215
Vuser Script Log .....	1216
Rendezvous Points .....	1217
Rendezvous Points Overview .....	1218
How to Set Up a Rendezvous in a Scenario .....	1218
Rendezvous Information Dialog Box .....	1219
After the Scenario Run .....	1221
Post Scenario Run Procedures - Overview .....	1221
Collating Run Data .....	1221
How to Collate Scenario Run Results .....	1222
Results Folder File Structure .....	1222
Collate Results Dialog Box .....	1224
Using QuickTest or Unified Functional Testing Tests in LoadRunner .....	1225
Using QuickTest or Unified Functional Testing Tests in LoadRunner - Overview .....	1225
About GUI Vuser Scripts .....	1225
Understanding GUI Vuser Technology .....	1226
Guidelines for Using QuickTest or Unified Functional Testing Tests in LoadRunner .....	1227
How to Add a QuickTest or Unified Functional Testing Test to a Load Test Scenario .....	1228
Managing Scenarios Using Application Lifecycle Management .....	1229
Managing Scenarios Using Application Lifecycle Management - Overview .....	1229
How to Work with Scenarios in ALM Projects .....	1229
Connect to ALM .....	1229
How to Save Scenarios to ALM Projects .....	1230

How to Add Vuser Scripts from an Application Lifecycle Management Project ...	1230
HP ALM Connection Dialog Box [Controller] .....	1231
Working with Firewalls in LoadRunner .....	1232
Monitors Over a Firewall .....	1233
How to Set Up Your System to Use Firewalls .....	1233
How to Configure the Over-Firewall System .....	1234
How to Configure the System to Monitor Servers Over a Firewall .....	1237
How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine ...	1238
How to Configure Monitors Over a Firewall .....	1240
Agent Configuration Dialog Box .....	1241
Agent Configuration Settings Dialog Box .....	1243
Authentication Settings Dialog Box .....	1244
MI Listener and Over Firewall Overview .....	1245
MI Listener Configuration Dialog Box .....	1247
Monitor Configuration Dialog Box .....	1248
Troubleshooting and Limitations - Firewalls .....	1250
Working with Diagnostics .....	1253
Configuring J2EE/.NET Diagnostics .....	1253
J2EE/.NET Diagnostics Overview .....	1254
Monitoring Server Requests .....	1254
How to Specify J2EE/.NET Diagnostics Server Details .....	1254
How to Configure a LoadRunner Scenario to use J2EE/.NET Diagnostics .....	1254
How to View J2EE/.NET Diagnostics Data in LoadRunner During a Scenario Run .....	1255
How to View Offline J2EE/.NET Diagnostics Results .....	1256
Diagnostics for J2EE/.NET Setup Dialog Box .....	1256
J2EE/.NET Configuration Dialog Box .....	1257
Monitoring Load Test Scenarios .....	1258
HP Performance Monitoring Best Practices Guide .....	1258
Working with LoadRunner Online Monitors .....	1258
Monitoring Process Overview .....	1258
How to Set Up a Monitoring Environment .....	1259

Monitor Types .....	1262
Add Machine Dialog Box .....	1263
<Monitor Type> Monitor Configuration Dialog Box .....	1264
<monitor name> Dialog Box .....	1265
Runtime and Transaction Monitoring .....	1266
Runtime Graphs Overview .....	1266
Transaction Monitor Graphs Overview .....	1267
Web Resource Monitors .....	1268
Web Resource Monitoring Overview .....	1268
WebSocket Statistics Monitor .....	1271
HTTP Status Codes .....	1272
System Resource Monitoring .....	1273
System Resource Monitors Overview .....	1273
Windows Resource Monitoring .....	1273
UNIX Resource Monitoring .....	1274
SNMP Resource Monitoring .....	1274
How to Set up the UNIX Monitoring Environment .....	1274
UNIX Resources Performance Counters .....	1276
Add Windows Resources Measurements Dialog Box .....	1277
Network Delay Monitoring .....	1277
Network Monitoring Overview .....	1277
How to Set Up the Network Monitoring Environment .....	1278
How to Configure the Linux Source Machine for Network Monitoring .....	1280
Adding Destination Machines for Network Delay Monitoring Dialog Box .....	1281
Network Delay Time Dialog Box .....	1282
Network Delay Time Graph .....	1283
Network Monitor Settings for Defined Path Dialog Box .....	1283
Troubleshooting and Limitations - Network Delay Monitor .....	1284
Web Server Resource Monitoring .....	1286
Web Server Resource Monitoring Overview .....	1286
How to change the Apache default server properties .....	1286

HTTP Status Codes .....	1286
Microsoft IIS Performance Counters .....	1287
Apache Performance Counters .....	1288
Web Application Server Monitoring .....	1289
Web Application Server Resource Monitoring Overview .....	1289
MS Active Server Pages Performance Counters .....	1289
Microsoft Active Server Pages Dialog Box .....	1290
Database Server Resource Monitoring .....	1290
Database Resource Monitoring Overview .....	1290
How to Set Up the Oracle Monitoring Environment .....	1291
Oracle Performance Counters .....	1293
SQL Server Performance Counters .....	1294
Configuring Oracle JDBC Monitor Dialog Box .....	1295
Shunra Network Virtualization Monitoring .....	1296
Average Latency Monitor .....	1296
Packet Loss Monitor .....	1297
Average Throughput Monitor .....	1299
Average Bandwidth Utilization Monitor .....	1301
Total Throughput Monitor .....	1302
SiteScope Server Monitoring .....	1303
SiteScope Resource Monitoring .....	1304
Flex Monitoring .....	1304
Streaming Media Monitoring .....	1304
Streaming Media Monitoring Overview .....	1304
RealPlayer Client Performance Counters .....	1305
Media Player Client Performance Counters .....	1305
ERP/CRM Server Resource Monitoring .....	1306
ERP/CRM Server Resource Monitoring Overview .....	1306
Siebel Server Manager Performance Counters .....	1306
Siebel Server Manager Configuration Dialog Box .....	1308
Troubleshooting and Limitations - Siebel Server Manager Monitor .....	1308

Application Deployment Solution Monitoring .....	1309
Application Deployment Solution Monitoring Overview .....	1309
How to Set up the Citrix Monitoring Environment .....	1309
Citrix MetaFrame Performance Counters .....	1310
Citrix Monitor Dialog Box .....	1315
Middleware Performance Monitoring .....	1315
Middleware Performance Monitoring Overview .....	1316
How to Set Up the IBM WebSphere MQ Monitor .....	1316
IBM WebSphere MQ Performance Counters .....	1317
IBM WebSphere MQ Queue Attributes .....	1319
MQ Monitor Add Measurements Dialog Box .....	1320
Infrastructure Resources Monitoring .....	1322
Infrastructure Resources Monitoring Overview .....	1322
Network Client Performance Counters .....	1322
Service Virtualization Integration .....	1322
HP Service Virtualization Integration - Overview .....	1322
Virtual Service Locks .....	1325
Service Virtualization Monitoring Overview .....	1325
How to Use Service Virtualization when Designing Scenarios .....	1327
Service Virtualization User Interface .....	1329
Appendices .....	1331
Secure Host Communication .....	1331
Secure Host Communication Overview .....	1331
Host Security Configuration .....	1333
Remote Security Configuration .....	1333
Host Security Best Practices .....	1334
How to Configure Security Settings Locally on Hosts .....	1335
How to Register Hosts in Host Security Manager .....	1336
How to Update Host Security Settings Remotely .....	1336
How to Change a Certificate .....	1338
Add Hosts Dialog Box .....	1338

Host Security Manager Window .....	1339
Host Security Setup Dialog Box .....	1340
Update Security Key Dialog Box .....	1341
Update Security Mode Dialog Box .....	1342
Troubleshooting and Limitations - Secure Host Communication .....	1342
Controller Command Line Arguments .....	1343
Controller Command Line Arguments Overview .....	1343
Invoke the Controller from the Command Line .....	1343
Command Line Arguments - Rules .....	1344
Application Lifecycle Management Arguments .....	1344
Run Time Arguments .....	1345
Working with Digital Certificates .....	1345
Digital Certificates Overview .....	1345
Using Digital Certificates with Firewalls .....	1346
How to Create and Use Digital Certificates .....	1346
Troubleshooting and Limitations - Controller .....	1348
Analysis .....	1350
Working with Analysis .....	1350
Introduction to Analysis .....	1350
Analysis Overview .....	1350
Analysis Basics .....	1351
Analysis Graphs .....	1352
Analysis API .....	1354
Network Virtualization .....	1354
How to Customize the Layout of Analysis Windows .....	1354
Analysis Toolbars .....	1355
Session Explorer Window .....	1357
Open a New Graph Dialog Box .....	1359
Print Graphs or Reports .....	1360
Configuring Analysis .....	1361
Summary Data Versus Complete Data .....	1361

Importing Data Directly from the Analysis Machine .....	1361
How to Configure Settings for Analyzing Load Test Results .....	1363
General Tab (Options Dialog Box) .....	1363
Result Collection Tab (Options Dialog Box) .....	1366
Data Aggregation Configuration Dialog Box (Result Collection Tab) .....	1369
Database Tab (Options Dialog Box) .....	1370
Advanced Options Dialog Box (Database Tab) .....	1375
Web Page Diagnostics Tab (Options Dialog Box) .....	1375
Session Information Dialog Box (Options Dialog Box) .....	1376
Configuring Graph Display .....	1378
How to Customize the Analysis Display .....	1378
Display Options Dialog Box .....	1378
Editing Main Chart Dialog Box (Display Options Dialog Box) .....	1380
Chart Tab (Editing MainChart Dialog Box) .....	1381
Series Tab (Editing MainChart Dialog Box) .....	1382
Legend Window .....	1383
Measurement Description Dialog Box .....	1386
Measurement Options Dialog Box .....	1387
Legend Columns Options Dialog Box .....	1388
Apply/Edit Template Dialog Box .....	1389
Color Palettes .....	1391
Color Palette Dialog Box .....	1391
Filtering and Sorting Graph Data .....	1394
Filtering Graph Data Overview .....	1394
Sorting Graph Data Overview .....	1395
Filter Conditions .....	1395
Custom Filter Dialog Box .....	1404
Filter Dialog Boxes .....	1405
Filter Builder Dialog Box .....	1407
Hierarchical Path Dialog Box .....	1408
Scenario Elapsed Time Dialog Box .....	1409

Set Dimension Information Dialog Box .....	1409
Vuser ID Dialog Box .....	1410
Working with Analysis Graph Data .....	1411
Determining a Point's Coordinates .....	1412
Drilling Down in a Graph .....	1412
Changing the Granularity of the Data .....	1414
Viewing Measurement Trends .....	1415
Auto Correlating Measurements .....	1416
Viewing Raw Data .....	1417
How to Manage Graph Data .....	1417
Drill Down Options Dialog Box .....	1419
Auto Correlate Dialog Box .....	1420
Graph/Raw Data View Table .....	1423
Graph Properties Window .....	1424
Viewing Load Test Scenario Information .....	1426
Viewing Load Test Scenario Information .....	1426
How to Configure Controller Output Messages Settings .....	1427
Controller Output Messages Window .....	1427
Summary Tab .....	1428
Filtered Tab .....	1430
Scenario Run Time Settings Dialog Box .....	1432
Cross Result and Merged Graphs .....	1432
Cross Result and Merged Graphs Overview .....	1432
Cross Result Graphs Overview .....	1433
Merging Types Overview .....	1434
How to Generate Cross Results Graphs .....	1436
How to Generate Merged Graphs .....	1436
Merge Graphs Dialog Box .....	1437
Defining Service Level Agreements .....	1437
Service Level Agreements Overview .....	1438
Tracking Period .....	1438

How to Define Service Level Agreements .....	1439
How to Define Service Level Agreements - Use-Case Scenario .....	1440
Service Level Agreement Pane .....	1443
Advanced Options Dialog Box (Service Level Agreement Pane) .....	1443
Goal Details Dialog Box (Service Level Agreement Pane) .....	1444
Service Level Agreement Wizard .....	1445
Select a Measurement Page .....	1445
Select Transactions Page .....	1446
Set Load Criteria Page .....	1447
Set Percentile Threshold Values Page .....	1448
Set Threshold Values Page (Goal Per Time Interval) .....	1449
Set Threshold Values Page (Goal Per Whole Run) .....	1450
Working with Application Lifecycle Management .....	1451
Managing Results Using ALM - Overview .....	1451
How to Connect to ALM .....	1451
How to Work with Results in ALM - Without Performance Center .....	1452
How to Work with Results in ALM - With Performance Center .....	1453
How to Upload a Report to ALM .....	1455
HP ALM Connection Dialog Box .....	1456
Upload Report to Test Lab Dialog Box .....	1458
Analysis Graphs .....	1459
Transaction Graphs .....	1459
Transaction Graphs Overview .....	1459
Average Transaction Response Time Graph .....	1459
Total Transactions per Second Graph .....	1461
Transaction Breakdown Tree .....	1462
Transactions per Second Graph .....	1463
Transaction Performance Summary Graph .....	1464
Transaction Response Time (Distribution) Graph .....	1465
Transaction Response Time (Percentile) Graph .....	1466
Transaction Response Time (Under Load) Graph .....	1467

Transaction Summary Graph .....	1468
Flex Graphs .....	1469
Flex RTMP Throughput Graph .....	1469
Flex RTMP Other Statistics Graph .....	1470
Flex RTMP Connections Graph .....	1471
Flex Streaming Delivery Graph .....	1471
Flex Average Buffering Time Graph .....	1472
Service Virtualization .....	1473
Service Virtualization Graphs Overview .....	1473
HP Service Virtualization Operations Graph .....	1473
HP Service Virtualization Services Graph .....	1474
Vuser Graphs .....	1475
Vuser Graphs Overview .....	1475
Rendezvous Graph (Vuser Graphs) .....	1475
Running Vusers Graph .....	1476
Vuser Summary Graph .....	1477
Error Graphs .....	1478
Error Graphs Overview .....	1478
Errors per Second (by Description) Graph .....	1478
Errors per Second Graph .....	1479
Error Statistics (by Description) Graph .....	1480
Error Statistics Graph .....	1481
Total Errors per Second Graph .....	1482
Web Resources Graphs .....	1483
Web Resources Graphs Overview .....	1483
Hits per Second Graph .....	1483
Throughput Graph .....	1484
HTTP Status Code Summary Graph .....	1485
HTTP Status Codes .....	1486
HTTP Responses per Second Graph .....	1488
Pages Downloaded per Second Graph .....	1489

Retries per Second Graph .....	1491
Retries Summary Graph .....	1492
Connections Graph .....	1492
Connections per Second Graph .....	1493
SSLs per Second Graph .....	1494
User-Defined Data Point Graphs .....	1495
User-Defined Data Point Graphs Overview .....	1495
Data Points (Average) Graph .....	1496
Data Points (Sum) Graph .....	1497
Network Monitor Graphs .....	1498
Network Monitor Graphs Overview .....	1498
Network Delay Time Graph .....	1499
Network Segment Delay Graph .....	1500
Network Sub-Path Time Graph .....	1501
Web Page Diagnostics Graphs .....	1502
Web Page Diagnostics Tree View Overview .....	1502
Web Page Diagnostics Graphs Overview .....	1502
How to View the Breakdown of a Transaction .....	1504
Web Page Diagnostics Content Icons .....	1505
Web Page Diagnostics Graph .....	1505
Page Component Breakdown Graph .....	1507
Page Component Breakdown (Over Time) Graph .....	1509
Page Download Time Breakdown Graph .....	1510
Page Download Time Breakdown (Over Time) Graph .....	1512
Page Download Time Breakdown Graph Breakdown Options .....	1514
Time to First Buffer Breakdown Graph .....	1515
Time to First Buffer Breakdown (Over Time) Graph .....	1517
Client Side Breakdown (Over Time) Graph .....	1519
Client Side Java Script Breakdown (Over Time) Graph .....	1520
Downloaded Component Size Graph .....	1521
System Resource Graphs .....	1522

System Resource Graphs Overview .....	1523
Server Resources Performance Counters .....	1523
Linux Resources Default Measurements .....	1523
Windows Resources Default Measurements .....	1524
Server Resources Graph .....	1526
Host Resources Graph .....	1527
SiteScope Graph .....	1528
SNMP Resources Graph .....	1529
Linux Resources Graph .....	1530
Windows Resources Graph .....	1531
Network Virtualization Graphs .....	1532
Packet Loss Graph .....	1532
Average Latency Graph .....	1534
Average Bandwidth Utilization Graph .....	1536
Average Throughput Graph .....	1537
Total Throughput Graph .....	1539
Firewall Server Graphs .....	1540
Firewall Server Monitor Graphs Overview .....	1540
Check Point FireWall-1 Server Measurements .....	1540
Check Point FireWall-1 Server Graph .....	1541
Web Server Resource Graphs .....	1541
Web Server Resource Graphs Overview .....	1542
Apache Server Measurements .....	1542
IIS Server Measurements .....	1542
Apache Server Graph .....	1543
Microsoft Information Internet Server (IIS) Graph .....	1544
Web Application Server Resource Graphs .....	1545
Web Application Server Resource Graphs Overview .....	1545
Web Application Server Resource Graphs Measurements .....	1546
Microsoft Active Server Pages (ASP) Graph .....	1553
Oracle9iAS HTTP Server Graph .....	1553

WebLogic (SNMP) Graph .....	1554
WebSphere Application Server Graph .....	1554
Database Server Resource Graphs .....	1554
Database Server Resource Graphs Overview .....	1554
DB2 Database Manager Counters .....	1555
DB2 Database Counters .....	1556
DB2 Application Counters .....	1561
Oracle Server Monitoring Measurements .....	1566
SQL Server Default Counters .....	1567
Sybase Server Monitoring Measurements .....	1568
DB2 Graph .....	1572
Oracle Graph .....	1573
SQL Server Graph .....	1573
Sybase Graph .....	1574
Streaming Media Graphs .....	1575
Streaming Media Graphs Overview .....	1575
Media Player Client Monitoring Measurements .....	1575
RealPlayer Client Monitoring Measurements .....	1576
RealPlayer Server Monitoring Measurements .....	1577
Windows Media Server Default Measurements .....	1578
Media Player Client Graph .....	1579
Real Client Graph .....	1579
Real Server Graph .....	1580
Windows Media Server Graph .....	1581
ERP/CRM Server Resource Graphs .....	1581
ERP/CRM Server Resource Graphs Overview .....	1582
ERP/CRM Server Resources Graphs Measurements .....	1582
Tuxedo Graph .....	1588
SAP Graph .....	1589
SAPGUI Graph .....	1590
SAP CCMS Graph .....	1591

SAP Portal Graph .....	1592
Siebel Server Manager Graph .....	1593
Siebel Web Server Graph .....	1594
Application Component Graphs .....	1595
Microsoft COM+ Performance Graphs Overview .....	1595
Microsoft .NET CLR Performance Graphs Overview .....	1595
COM+ Average Response Time Graph .....	1596
COM+ Breakdown Graph .....	1597
COM+ Call Count Distribution Graph .....	1599
COM+ Call Count Graph .....	1601
COM+ Call Count Per Second Graph .....	1602
COM+ Total Operation Time Distribution Graph .....	1603
COM+ Total Operation Time Graph .....	1605
Microsoft COM+ Graph .....	1606
.NET Average Response Time Graph .....	1609
.NET Breakdown Graph .....	1610
.NET Call Count Distribution Graph .....	1612
.NET Call Count Graph .....	1612
.NET Call Count per Second Graph .....	1613
.NET Resources Graph .....	1614
.NET Total Operation Time Distribution Graph .....	1618
.NET Total Operation Time Graph .....	1619
Application Deployment Solutions Graphs .....	1619
Application Deployment Solutions Graph Overview .....	1620
Citrix Measurements .....	1620
Citrix MetaFrame XP Graph .....	1624
Middleware Performance Graphs .....	1625
Middleware Performance Graphs Overview .....	1625
IBM WebSphere MQ Counters .....	1625
Tuxedo Resources Graph Measurements .....	1627
IBM WebSphere MQ Graph .....	1629

Tuxedo Resources Graph .....	1630
Infrastructure Resources Graphs .....	1631
Infrastructure Resources Graphs Overview .....	1631
Network Client Measurements .....	1631
Network Client Graph .....	1632
Analysis Reports .....	1632
Understanding Analysis Reports .....	1632
Analyze Transaction Settings Dialog Box .....	1633
Analyze Transactions Dialog Box .....	1634
New Report Dialog Box .....	1636
Analysis Report Templates .....	1637
Report Templates Overview .....	1637
Report Templates Dialog Box .....	1637
Report Templates - General Tab .....	1639
Report Templates - Format Tab .....	1640
Report Templates - Content Tab .....	1642
Analysis Report Types .....	1644
Summary Report Overview .....	1644
Summary Report .....	1644
HTML Report .....	1649
SLA Reports .....	1650
Transaction Analysis Report .....	1651
Analysis Reports Overview .....	1652
Importing External Data .....	1653
Import Data Tool Overview .....	1653
How to Use the Import Data Tool .....	1653
How to Define Custom File Formats .....	1655
Supported File Types .....	1655
Advanced Settings Dialog Box (Import Data Dialog Box) .....	1657
Define External Format Dialog Box .....	1658
Import Data Dialog Box .....	1659

Siebel Diagnostics Graphs .....	1661
Siebel Diagnostics Graphs Overview .....	1661
How to Enable Siebel Diagnostics .....	1662
Call Stack Statistics Window .....	1663
Chain of Calls Window .....	1665
Siebel Area Average Response Time Graph .....	1666
Siebel Area Call Count Graph .....	1667
Siebel Area Total Response Time Graph .....	1668
Siebel Breakdown Levels .....	1669
Siebel Diagnostics Graphs Summary Report .....	1673
Siebel Request Average Response Time Graph .....	1673
Siebel Transaction Average Response Time Graph .....	1674
Working with Diagnostics .....	1675
Siebel DB Diagnostics Graphs .....	1675
Siebel DB Diagnostics Graphs Overview .....	1675
How to Enable Siebel DB Diagnostics .....	1676
How to Synchronize Siebel Clock Settings .....	1677
Measurement Description Dialog Box .....	1677
Siebel Database Breakdown Levels .....	1678
Siebel Database Diagnostics Options Dialog Box .....	1682
Siebel DB Side Transactions Graph .....	1683
Siebel DB Side Transactions by SQL Stage Graph .....	1683
Siebel SQL Average Execution Time Graph .....	1684
Oracle 11i Diagnostics Graphs .....	1684
Oracle 11i Diagnostics Graphs Overview .....	1684
How to Enable Oracle 11i Diagnostics .....	1685
Measurement Description Dialog Box .....	1686
Oracle Breakdown Levels .....	1687
Oracle 11iDB Side Transactions Graph .....	1689
Oracle 11iDB Side Transactions by SQL Stage Graph .....	1690
Oracle 11i SQL Average Execution Time Graph .....	1690

SAP Diagnostics Graphs .....	1691
SAP Diagnostics Graphs Overview .....	1691
How to Enable SAP Diagnostics .....	1691
How to Configure SAP Alerts .....	1692
SAP Diagnostics - Guided Flow Tab .....	1693
SAP Diagnostics Application Flow .....	1694
Dialog Steps per Second Graph .....	1695
OS Monitor Graph .....	1695
SAP Alerts Configuration Dialog box .....	1696
SAP Alerts Window .....	1696
SAP Application Processing Time Breakdown Graph .....	1698
SAP Primary Graphs .....	1698
SAP Average Dialog Step Response Time Breakdown Graph .....	1698
SAP Average Transaction Response Time Graph .....	1699
SAP Breakdown Task Pane .....	1700
SAP Server Time Breakdown (Dialog Steps) Graphs .....	1703
SAP Server Time Breakdown Graph .....	1703
SAP Database Time Breakdown Graph .....	1704
SAP Diagnostics Summary Report .....	1705
SAP Interface Time Breakdown Graph .....	1706
SAP System Time Breakdown Graph .....	1706
SAP Secondary Graphs .....	1707
Work Processes Graph .....	1707
J2EE & .NET Diagnostics Graphs .....	1708
J2EE & .NET Diagnostics Graphs Overview .....	1708
How to Enable Diagnostics for J2EE & .NET .....	1708
Viewing J2EE to SAP R3 Remote Calls .....	1709
J2EE & .NET Diagnostics Data .....	1710
Example Transaction Breakdown .....	1711
Using the J2EE & .NET Breakdown Options .....	1715
Viewing Chain of Calls and Call Stack Statistics .....	1717

The Chain of Calls Windows .....	1718
Understanding the Chain of Calls Window .....	1719
Graph Filter Properties .....	1721
J2EE/.NET - Average Method Response Time in Transactions Graph .....	1722
J2EE/.NET - Average Number of Exceptions in Transactions Graph .....	1723
J2EE/.NET - Average Number of Exceptions on Server Graph .....	1724
J2EE/.NET - Average Number of Timeouts in Transactions Graph .....	1724
J2EE/.NET - Average Number of Timeouts on Server Graph .....	1725
J2EE/.NET - Average Server Method Response Time Graph .....	1726
J2EE/.NET - Method Calls per Second in Transactions Graph .....	1727
J2EE/.NET - Probes Metrics Graph .....	1728
J2EE/.NET - Server Methods Calls per Second Graph .....	1729
J2EE/.NET - Server Requests per Second Graph .....	1730
J2EE/.NET - Server Request Response Time Graph .....	1731
J2EE/.NET - Server Request Time Spent in Element Graph .....	1732
J2EE/.NET - Transactions per Second Graph .....	1734
J2EE/.NET - Transaction Response Time Server Side Graph .....	1734
J2EE/.NET - Transaction Time Spent in Element Graph .....	1735
Troubleshooting and Limitations - Analysis .....	1736
LoadRunner Guides and References .....	1739
Additional Components .....	1741
Third Party Components .....	1743

# Welcome to the LoadRunner User Guide

Welcome to LoadRunner, the HP solution for application performance testing. LoadRunner stresses your entire application to isolate and identify potential client, network, and server bottlenecks.

LoadRunner includes:

- **VuGen.** HP's tool for creating Vuser scripts. You use VuGen to develop a Vuser script by recording a user performing typical business processes. The scripts let you emulate real-life situations.
- **Controller.** Allows you to easily and effectively control all the Vusers from a single point of control and monitor the scenario performance during test execution.
- **Analysis.** You use Analysis after running a load test scenario in the HP LoadRunner Controller or HP Performance Center. The Analysis graphs help you determine system performance and provide information about transactions and Vusers. You can compare multiple graphs by combining results from several load test scenarios or merging several graphs into one.

## LoadRunner Online Help

LoadRunner Help is an online help system that describes how to use LoadRunner. You can access the LoadRunner Help in the following ways:

- Select HP Virtual User Generator Help, HP Controller Help, or HP Analysis Help from the **Help** menu of any of the LoadRunner components to open the LoadRunner Help home page. The home page provides quick links to the main help topics.
- Click F1 on any window or dialog box to open the LoadRunner Help to the topic that describes the currently displayed screen.
- Use the Help menu in LoadRunner to access the Knowledge Base and other useful resources.

## Additional Online Resources

The following online resources provide more information for LoadRunner users:

Resource	URL
<b>HP Software Web site</b>	<a href="http://www.hp.com/go/software">http://www.hp.com/go/software</a>
<b>HP Software Support</b>	<a href="http://www.hp.com/go/hpsoftwaresupport">http://www.hp.com/go/hpsoftwaresupport</a>
<b>Troubleshooting &amp; Knowledge Base</b>	<a href="http://h20230.www2.hp.com/troubleshooting.jsp">http://h20230.www2.hp.com/troubleshooting.jsp</a>
<b>LoadRunner Community Forums</b>	<a href="http://www.hp.com/go/lrcf">http://www.hp.com/go/lrcf</a>

Resource	URL
<b>LoadRunner Blog</b>	<a href="http://h30499.www3.hp.com/t5/HP-LoadRunner-and-Performance/bg-p/sws-585">http://h30499.www3.hp.com/t5/HP-LoadRunner-and-Performance/bg-p/sws-585</a>
<b>HP Live Network (HPLN)</b>	<a href="https://hpln.hp.com/group/performance-center-and-loadrunner">https://hpln.hp.com/group/performance-center-and-loadrunner</a>
<b>LoadRunner Integrations</b>	<a href="http://support.openview.hp.com/sc/solutions/index.jsp#tab=tab1">http://support.openview.hp.com/sc/solutions/index.jsp#tab=tab1</a>
<b>LoadRunner on Twitter</b> 	<a href="https://twitter.com/hploadrunner">https://twitter.com/hploadrunner</a>
<b>LoadRunner on Linked In</b> 	<a href="http://www.linkedin.com/groups?home=&amp;gid=1879289">http://www.linkedin.com/groups?home=&amp;gid=1879289</a>

# What's New in LoadRunner 12.00

## Ability to run load generators on the cloud

- Easily provision cloud load generators from the Controller. For details, see "[Adding a Cloud-Based Load Generator - Overview](#)" on page 1076.
- Run tests on load generators on the Amazon cloud

## Enhanced communication interface between Controller and load generators

- Ability to configure the ports between all LoadRunner components—Controller, load generator, MI Listener, and Monitor over Firewall
- Ability to connect from Controller to load generator, MI Listener, and Monitor over Firewall via proxy
- Use of Network Connection profiles that let you configure connection information, such as port and proxy, separately for each load generator For details, see "[Network Profile Manager Dialog Box](#)" on page 1104.
- Improved support and enhanced usability for SSL security
- Ability to configure load generator to accept communication only from trusted Controllers using SSL authentication

## Network and security manager

- New utility to configure network and security settings for LoadRunner agent, for both local and remote machines. For details, see "[Network and Security Manager - Command Line Tool](#)" on page 1108.

## Enhancements for testing mobile applications

- Replay support for SMP (SAP Mobile Platform) recorded sessions. For details, see "[How to create an SMP \(SAP Mobile Platform\) script](#)" on page 717.
- Enhanced proxy recording. For details, see "[How to Record a Script via a Proxy](#)" on page 261.

## Improvements and added features in VuGen

- Enhanced replay summary with transaction breakdown with new time- trend charts. For details see "[Replay Summary Tab](#)" on page 140.
- Support for editing common file types in VuGen editor—not limited to Vuser scripts
- Multiple VuGen usability improvements for better productivity

- Ability to cancel a recording session without overwriting script
- Improved search capabilities
- Debugger improvements

## Enhancements and added integrations for protocols

- **Web HTTP/HTML:**
  - HTML5 WebSocket support. For details, see the [web\\_websocket](#) functions in the [LoadRunner Function Reference](#).
  - TruClient to Web HTTP/HTML protocol script converter. For details, see "[Converting a TruClient Script to a Web HTTP/HTML Script](#)" on page 567.
  - SSL utility for performing various *OpenSSL* commands through a user-friendly interface. For details, see "[SSL Utility](#)" on page 1114.
  - SPDY support. For details, see "[How to record the SPDY protocol](#)" on page 815.
  - Internet Explorer 11 support
  - TLS 1.1, TLS 1.2, and NPN support
  - Enhanced asynchronous support with ResponseHeader callback
  - Recording troubleshooting: ability to identify recording failure and suggest a possible fix
- **Linux support:** Replay support on Linux-based load generators was added for the following protocols: FTP, IMAP, LDAP, POP3, SMTP, and Windows Sockets
- **TruClient:** Support for rendezvous points, IP spoofing, VTS, and Shunra network virtualization
- **Silverlight:** Support for latest version and IP Spoofing
- **SAP-Web:** Correlation Studio support in VuGen
- **LDAP:** Support for latest version of LDAP SDK
- **Flex:** Support for the latest Apache SDK
- **.NET:** Support for version 4.5
- **Citrix:** Support for latest client receiver, ability to run multiple published applications in the same session, and latest XenDesktop support
- **SAP:** The SAP Application Testing by HP, HANA Edition (LoadRunner and Quality Center/Application Lifecycle Management) has received a Premium Qualification for SAP Vendor Branded Resellers. This certification is effective from LoadRunner 11.50 and Application

Lifecycle Management 11.00.

## New supported technologies and platforms

- Windows Server 2012 support
- Record and replay support for Internet Explorer 11, Chrome version 30, and Firefox version 23
- Support for latest versions of Eclipse, JUnit, and Selenium

## External IDE integration/add-ins for LoadRunner scripts and applications

- Ability to invoke the Controller directly from Visual Studio and Eclipse
- Add-in for Visual Studio 2012 for VuGen scripts and unit test developers
- Support for latest version of Eclipse

For details, see "[Additional Components](#)" on page 1741.

## Improvements in Virtual Table Server (VTS)

- Create multiple running instances of VTS
- Run VTS commands and batch files from the command line
- VTS support through a JavaScript API
- Populate data tables with sample data from the main menu

For details, see the Virtual Table Server documentation.

## Integration with latest HP product versions

- HP Service Virtualization
- HP Diagnostics
- HP SiteScope
- HP Unified Functional Testing (UFT)
- HP Application Lifecycle Management (ALM)

## Improved documentation

- Workflow diagrams added to user guide for testing and script creation processes
- Enhancements to Flex, Web HTTP/HTML, and TruClient protocol documentation, with added tasks and procedures

- Improved organization of function reference including additional code samples and the new WebSocket functions

## General enhancements

- Simplified product installation with shorter installation time
- Non-admin user support: LoadRunner components can now run under a standard user account and with UAC and DEP enabled—an administrator account is no longer required. This applies to all LoadRunner components and tools accessible from the **LoadRunner > Tools** node under the Start menu.
- Shunra integration enhancements
- Database API functions are now available for all C language protocols

## Community license bundle

- LoadRunner now delivered with the Community bundle which replaces the Instant-on license
  - The new bundle is permanent, with 50 Vusers
  - Included are all the protocols except for GUI (UFT), COM/DCOM and protocols in the template bundle

For a complete list of supported integrations and product versions, see the Software Support site at [www.hp.com/go/hpsoftwaresupport](http://www.hp.com/go/hpsoftwaresupport), or select **Help > HP Software Support Online**. Click the **Self-solve** tab, and search for the LoadRunner PAM (Product Availability Matrix) for this version.

## VuGen Concepts

The **VuGen Concepts** section provides information about various topics relating to the use of VuGen to create Vuser scripts.

## VuGen - Overview

When testing or monitoring an environment, you need to emulate the true behavior of users on your system. HP testing tools emulate an environment in which users concurrently work on, or access your system. To perform this emulation, the human was replaced with a virtual user, or a *Vuser*. The actions that a Vuser performs are typically recorded in a *Vuser script*. The primary tool for creating Vuser scripts is HP's Virtual User Generator, also known as VuGen.

VuGen not only records Vuser scripts, but also runs them. Running scripts from VuGen is useful for debugging. It enables you to determine how a Vuser script will run when it is executed as part of a larger test.

When you record a Vuser script, VuGen generates various functions that define the actions that you perform during the recording session. VuGen inserts these functions into the VuGen editor to create a basic Vuser script.

VuGen records Vuser scripts on Windows platforms only. However, a recorded Vuser script can be run on both Windows and Linux platforms.


You can also program Vuser scripts in your native programming application such as MS Visual Studio. To access the LoadRunner API, install the appropriate IDE add-in provided on the LoadRunner DVD.

## Vuser Technology Overview

Vusers emulate the actions of human users by performing typical business processes in your application. The actions that a Vuser performs during the recording session are described in a *Vuser script*.

HP's tool for creating Vuser scripts is the Virtual User Generator, *VuGen*. You use VuGen to develop a Vuser script by recording a user performing typical business processes on a client application. VuGen records the actions that you perform during the recording session, recording only the activity between the client and the server. Instead of having to manually program the application's API function calls to the server, VuGen automatically generates functions that model and emulate real world situations.

During recording, VuGen monitors the client and traces all the requests sent to and received from the server.



During playback, Vuser scripts communicate directly with the server by executing calls to the server API. When a Vuser communicates directly with a server, system resources are not required for the client interface. This lets you run a large number of Vusers simultaneously on a single workstation, and enables you to use only a few testing machines to emulate large server loads.



In addition, since Vuser scripts do not rely on client software, you can use Vusers to check server performance even before the user interface of the client software has been fully developed.

Using VuGen, you can run scripts as standalone tests. This is useful for verifying the script's functionality and it enables you to see how a Vuser will behave during a test run.

To effectively use the Vuser scripts, you add them to a scenario using the LoadRunner Controller. While running the Vusers, you gather information about the system's response. Afterwards, you can view this information with the Analysis tool. For example, you can observe how a server behaved when one hundred Vusers simultaneously withdrew cash from a bank's ATM. For details, see "["LoadRunner Controller Overview" on page 1013](#)".

VuGen records Vuser scripts on Windows platforms only. However, a recorded Vuser script can be run on both Windows and Linux platforms.

## Vuser Types

LoadRunner supports several Vuser types:

### Protocol Based Vusers

LoadRunner supports various types of Vusers using the most common protocols. Each type is designed to handle different aspects of today's system architectures.

You can create a Vuser script using a single protocol or multiple ones.

For a complete list of the available Vuser protocols, see "["Vuser Protocols" below](#)".

## Unit Test Based Vusers

LoadRunner supports unit tests in the form of **.dll** or **.jar/.class** files, created in Microsoft Visual Studio or Eclipse.

To create these tests, install the appropriate IDE for Developer add-in, available in the **Additional Components** folder of the LoadRunner DVD.

## GUI Vusers

LoadRunner can integrate functional testing scripts in the form of *GUI tests* into a load testing scenario. You create GUI tests using HP Functional Testing software - QuickTest or Unified Functional Testing.

You can run only a single GUI Vuser on a Windows-based load generator. Use Citrix to run multiple GUI Vusers. For additional information on Windows-based GUI Vusers, see "["Using QuickTest or Unified Functional Testing Tests in LoadRunner" on page 1225](#)".

# Vuser Protocols

VuGen enables you to record a variety of protocols, each suited to a particular load testing environment or topology and results in a specific type of Vuser script. For example, you can use a Web (HTTP/HTML) Vuser Script to emulate users operating Web browsers. You can use FTP Vusers to emulate an FTP session. The various Vuser technologies can be used alone or together, to create effective load tests.

The following table lists the available Vuser protocols, and a brief description of each protocol.

**Note:** In the LoadRunner documentation, the terms *Vuser protocols* and *Vuser types* are used interchangeably.

Protocol	Description
.NET	Supports the recording of Microsoft .NET client-server technologies.
Ajax (Click & Script)	An acronym for Asynchronous JavaScript and XML. Ajax (Click & Script) uses asynchronous HTTP requests, allowing Web pages to request small bits of information instead of whole pages.
C Vuser	A generic virtual user which uses the standard C library.
Citrix ICA	A remote access tool, allowing users to run specific applications on external machines.
COM/DCOM	Component Object Model (COM) - a technology for developing reusable software components.

Protocol	Description
(DNS) Domain Name Resolution	The DNS protocol is a low-level protocol that allows you to emulate the actions of a user working against a DNS server. The DNS protocol emulates a user accessing a Domain Name Server to resolve a host name with its IP address. Only replay is supported for this protocol—you need to manually add the functions to your script.
Flex	Flex is an application development solution for creating Rich Internet Applications (RIAs) within the enterprise and across the Web. Action Message Format (AMF), is a Macromedia proprietary protocol that allows Flash Remoting binary data to be exchanged between a Flash application and an application server over HTTP.
FTP (File Transfer Protocol )	File Transfer Protocol - a system which transfers files from one location to another over a network. The FTP protocol is a low-level protocol that allows you to emulate the actions of a user working against an FTP server.
IMAP (Internet Messaging)	Internet Message Application - a protocol which enables clients to read email from a mail server.
Java over HTTP	Designed to record java-based applications and applets. It produces a Java language script using web functions. This protocol is distinguished from other Java protocols in that it can record and replay Java remote calls over HTTP.
Java Record Replay	Common Java recorder.
Java Vuser	Java programming language with protocol level support.
LDAP (Listing Directory Service)	An Internet protocol designed to allow email applications to look up contact information from a server.
MAPI (Microsoft Exchange)	Messaging Application Programming Interface designed to allow applications to send and receive email messages.
MMS (Media Player)	Streaming data from a media server using Microsoft's MMS protocol. <b>Important:</b> In order to replay Media Player functions, you must place a file called <code>wmload.asf</code> on the Windows Media server machine. The VuGen machine must be able to access it using <code>mms://&lt;servername&gt;/wmload.asf</code> . This ASF file can be any media file renamed to <code>wmload.asf</code> .
MMS (Multimedia Messaging Service)	A messaging service used for sending MMS messages between mobile devices.

Protocol	Description
Mobile Application - HTTP/HTML	Enables the recording of mobile native applications.
ODBC	Open Database Connectivity - a protocol providing a common interface for accessing databases.
Oracle - 2 Tier	Oracle database using a standard 2-tier client/server architecture.
Oracle Web Applications 11i	The Oracle Applications interface that performs actions over the Web. This Vuser type detects actions on both the LoadRunner API and Javascript levels.
Oracle NCA	Oracle 3-tier architecture database consisting of Java client, Web server and database.
POP3 (Post Office Protocol)	A protocol designed to allow single computers to retrieve email from a mail server.
RDP (Remote Desktop Protocol)	A remote access tool using the Microsoft Remote Desktop Connection to run applications on an external machine.
RTE (Remote Terminal Emulator)	Emulation of users who submit input to, and receive output from, character-based applications.
SAP (Click & Script)	Emulation of communication between a browser and SAP server on a GUI or user-action level.
SAP GUI	An Enterprise Resource Planning system to integrate key business and management processes using the SAP GUI client for Windows.
SAP - Web	An Enterprise Resource Planning system to integrate key business and management processes using the SAP Portal or Workplace clients.
Siebel - Web	A Customer Relationship Management Application.
Silverlight	A protocol for Silverlight based applications emulating user activity at the transport level. Allows generating high level scripts by automatically importing and configuring WSDL files used by the application.
SMP (SAP Mobile Platform)	A protocol for recording actions on a mobile SAP application.

Protocol	Description
SMTP (Simple Mail Protocol)	Simple Mail Transfer Protocol - a system for distributing mail to a particular machine.
TruClient - Ajax	An advanced protocol for modern JavaScript based applications (including Ajax) emulating user activity within a web browser. Scripts are developed interactively in Mozilla Firefox or Internet Explorer.
TruClient - Ajax - Mobile	Enables the recording of mobile browser based applications using the TruClient Ajax technology.
Web (HTTP/HTML)	Emulation of communication between a browser and Web server on an HTTP or HTML level.
Web Services	Web Services are a programmatic interface for applications to communicate with one another over the World Wide Web.
Windows Sockets	The standard network programming interface for the Windows platform.

**Note:** In order to use the Controller to run Vusers of the various protocols, you must have either a global license or licenses for the desired protocols. The Community Bundle Includes 50 Vusers for all protocols, except GUI (UFT), COM/DCOM and protocols in the template bundle, such as C Vuser. To check your Vuser licensing details, open the LoadRunner License Utility by selecting **Start > All Programs > HP Software > HP LoadRunner > License > LoadRunner License Utility**.

## Keyboard Shortcuts

The following tables list the keyboard shortcuts available for the VuGen menus:

### File Menu

New > Script and Solution	Ctrl+N
Open > Script/Solution	Ctrl+O
Add > New Script	Ctrl+Shift+A
Add > Existing Script	Alt+Shift+A
Close > Document	Ctrl+F4
Close > Solution	Ctrl+Shift+F4
Save Script	Ctrl+S
Save All Scripts	Ctrl+Shift+S

Reload File	Ctrl+Shift+U
Print	Ctrl+P
Exit	Alt+F4

## Edit Menu

Undo	Ctrl+Z
Redo	Ctrl+Y
Cut	Ctrl+X
Copy	Ctrl+C
Paste	Ctrl+V
Delete	Del
Select All	Ctrl+A
Format > Surround with	Ctrl+J
Format > Increase Indent	Tab
Format > Decrease Indent	Shift+Tab
Folding > Toggle fold	Ctrl+Shift+M
Folding > Toggle all folds	Ctrl+Shift+L
Folding > Show definitions only	Ctrl+Shift+P
Show Function Syntax	Ctrl+Shift+Space
Complete Word	Ctrl+Space

## View Menu

Solution Explorer	Ctrl+Alt+L
Search Results	Ctrl+Alt+R
Bookmarks	Ctrl+Alt+K
Steps Toolbox	Ctrl+Alt+B
Snapshot	Ctrl+Alt+P
Steps Navigator	Ctrl+Alt+S
Thumbnail Explorer	Ctrl+Alt+T

Properties	Ctrl+Alt+F4
Output	Ctrl+Alt+O
Full Screen	Alt+Shift+Return

## Search Menu

Quick Find	Ctrl+F
Find Next	F3
Find Next Selected	Ctrl+F3
Find in Files	Ctrl+Shift+F
Quick Replace	Ctrl+H
Incremental Search	Ctrl+E
Reverse Incremental Search	Ctrl+Shift+E
Bookmarks > Toggle Bookmark	Ctrl+F2
Bookmarks > Prev Bookmark	Shift+F2
Bookmarks > Next Bookmark	F2
Go To	Ctrl+G

## Design Menu

Action > Delete Action	Delete
Action > Rename Action	F2
Insert in Script > New Step	Alt+Insert
Insert in Script > Start Transaction	Ctrl+T
Insert in Script > End Transaction	Ctrl+Shift+T
Insert in Script > Comment	Ctrl+Alt+C
Parameters > Parameters List	Ctrl+L
Parameters > Create New Parameter	Ctrl+K
Parameters > Configure Parameter Delimiters	Ctrl+B
Design Studio	Ctrl+U

## Record Menu

Record	Ctrl+R
Regenerate Script	Ctrl+Shift+R
Recording Options	Ctrl+F7

## Replay Menu

Run	F5
Stop	Ctrl+F5
Compile	Shift+F5
Toggle Breakpoint	F9
Continue Debugging	F5
Run Step by Step	F10
Run-Time Settings	F4

## ALM

ALM Connection	Ctrl+Q
----------------	--------

## Windows Menu

Next Window	Ctrl+Tab
Prev Window	Ctrl+Shift+Tab


## IPv6 Support

As IPv6 implementation becomes more widespread, LoadRunner now enables you to test IPv6 based applications in addition to IPv4 based ones. Script recording supports recording for both IPv4 and IPv6 simultaneously. The code that is generated is non-IP specific. Except for Web HTTP based protocols, users will be unaware of which IP version is being used when replaying the script in a load test. Web HTTP protocols have a Runtime setting that allows you to choose between IPv4 and IPv6 for the replay.

### IPv6 Deployment

The internal LoadRunner communication between the Controller and Load Generators still uses IPv4 communication. To record and replay in both IPv4 and IPv6, install both VuGen and Load Generator on IPv6-enabled computers, as shown in the diagram below.

### IPv6 Deployment Changes



For more details about IPv6 related changes, see [Advanced Options Dialog Box](#) and the IP Wizard section in the *Controller User Guide*.

### Protocols Supported

The following protocols support IPv6 testing:

- Citrix ICA
- DNS
- Flex
- FTP
- IMAP
- Java over HTTP
- Mobile Application - HTTP/HTML
- Window Sockets - Multi protocol

- Oracle NCA
- POP3
- RDP
- Silverlight
- SMTP
- TruClient Ajax
- Click & Script family
- Web (HTTP/HTML)
- Web Services

## Protocol Support Limitations

Support for IPv6 is available for the protocols shown in the list above with the following limitations:

- **Web HTTP protocol**
  - FTP from Web is not supported
  - Web Breakdown is not supported
  - Kerberos is not supported
  - Spoofing from Web is not supported
  - PAC file is not supported
  - An explicit IP (in IPv6 format) in a URL argument cannot be used. For example, the following step will fail in replay:

```
web_url("IPv6",
"URL=http://[2001:0dc8:8aa3:0000:0b00:8a2e:0370:7334]/",
"Resource=0",
"RecContentType=text/html",
"Referer=",
"Snapshot=t1.inf",
```

"Mode=HTML",

LAST);

- Webtrace
  - IPv6 Webtrace is not supported on 6to4 outgoing network interfaces.
  - IPv6 webtrace does not support RawSocket mode
- **General limitations**
  - Replay failures may occur because of a IPv4/IPv6 switch between recording and replaying.

## VuGen User Interface

The **VuGen User Interface** section describes each component of the environment you will be working in while you record, replay, and debug a Vuser script.

### VuGen User Interface - Overview

The VuGen User Interface is comprised of several zones, each of which can display a variety of panes. You can modify the layout of these zones and panes to enhance recording and debugging of your Vuser scripts. For details, see "["VuGen Layouts - Overview" on page 79](#)".

The following table describes each pane and provides a short use case scenario.

Pane	Purpose	Use Case Scenario
<b>Bookmarks</b>	Bookmarks allow you to specify a location in a script so that you can easily find it later on for editing.  For details, see " <a href="#">"Bookmarks Pane" on page 131</a> ".	
<b>Errors</b>	Displays script errors, warnings and messages generated from script replay. Additionally, you can create custom filters for error messages.  For details, see " <a href="#">"Errors Pane" on page 133</a> ".	<b>Error Filter from the output log</b>  After every test process, such as code generation and replay, you can check the error pane for the error log. You can also view other types such as warning and message.  Community search is available with context menu on highlighted error.  In addition, you can double click the message to jump to the location in the script.

Pane	Purpose	Use Case Scenario
<b>Snapshot</b>	A snapshot displays server and client data associated with a specific step in a script. The format of the data is dependent on the protocol used for creating the script.  For Snapshot details, see " <a href="#">Snapshot Pane</a> " on page 126.	Use the snapshot pane to understand all data that the steps contain.  You can perform certain tasks such as search for correlations, compare record versus replay snapshots and search for the specific values using the standard search operation.
<b>Data Grid</b>	Simplified view of all the recordsets associated with the script. Valid for specific protocols such as MSSQL.	The data pane contains either sent or received data. The data is displayed in an easy formatted table and you perform operations such as parameterization, and other data manipulations.
<b>Solution Explorer</b>	The Solution Explorer enables you to organize and manage multiple scripts in a named solution.  This pane provides easy access and manipulation of solutions such as script assets, parameters, runtime settings, and replay runs.  You can double-click an asset to activate it in the editor area or right-click to examine quick operations available for that asset.  For details, see " <a href="#">Solution Explorer Pane</a> " on page 118.	You can now bundle scripts in a solution. For example you can bundle scripts related to one business process.  For the present, the solution entity is limited in the following ways: <ul style="list-style-type: none"> <li>• The solution entity is limited to local script development such as save all or open.</li> <li>• The solution entity can not be imported into any of the existing management tools such as ALM or Controller.</li> </ul>


Pane	Purpose	Use Case Scenario
<b>Step Navigator</b>	<p>Enables you to navigate to a selected step in your script. If your script contains many steps, you can use the search box to search for matching text in the different parts of the steps.</p> <p>For details, see "<a href="#">Step Navigator Pane</a>" on page 132.</p>	<p>Table view of all LoadRunner API steps that exist. The step navigator replaces the tree view in previous versions of VuGen.</p> <ul style="list-style-type: none"> <li>Dynamic filter on various step properties such as step arguments.</li> <li>You can view the script in either action or script scope.</li> <li>Every step that has a snapshot is marked with an icon. When hovering over a step that has an associated thumbnail it is presented as a tooltip.</li> <li>Double clicking a step, takes you to the corresponding location in the script and synchronizes all other panes.</li> <li>Various operations can be done from the context menu such as copy stop.</li> <li>Step Navigation is synchronized based on the validity of the script. You can check the status of the pane during script editing.</li> </ul>
<b>Tasks</b>	<p>You can add, edit or search for tasks related to a script or solution.</p> <p>For details, see "<a href="#">Task Pane</a>" on page 134.</p>	<p><b>Centralized Task Management</b></p> <p>During script development, comments tasks enable you to embed tasks in the script. For example in a C based language script, <code>//TODO Add Parameter</code></p> <p>User tasks enable you to add tasks, assign ownership and track completion of tasks related to the overall script process. For example, <b>Add Load Test Scenario using newly created script</b>.</p>

Pane	Purpose	Use Case Scenario
<b>Editor</b>	<p>The editor area contains all open assets such as script actions, extra files, report summary enables you to edit script actions.</p> <p>In addition you can open community search, help documentation, and browser pages.</p> <p>For details, see "<a href="#">"Editor" on page 112.</a></p>	<p>You can view script actions simultaneously from different scripts within a solution.</p> <ul style="list-style-type: none"> <li>• You can insert comment blocks.</li> <li>• You can customize the color scheme.</li> <li>• You can enlarge the fonts.</li> <li>• Auto-completion options using CTRL + SPACE.</li> <li>• All supportive data in the panes is synchronized as you navigate through the script.</li> <li>• The script support full debug capability can be managed within the script such as toggle breakpoints.</li> <li>• Community search is available on highlighted text in the script.</li> </ul>
<b>Thumbnail</b>	<p>Enables you to visually follow the business process that the script has recorded.</p> <p>For details, see "<a href="#">"Thumbnail Explorer" on page 113.</a></p>	<ul style="list-style-type: none"> <li>• The thumbnail generation is configurable in <b>Tools &gt; Options</b>.</li> <li>• You can enlarge the thumbnail to full size by double clicking.</li> <li>• Additional operations are available from the context menu such as <b>Go to Step</b>.</li> </ul>
<b>Output</b>	<p>Event log from different operations in VuGen such as code generation, replay, and recording.</p> <p>For details, <a href="#">"Output Pane" on page 124</a></p>	<p>The output pane displays all logs created during script development phases such as code generation, replay, and recording.</p> <ul style="list-style-type: none"> <li>• You can perform quick searches from the pane or access full search with CTRL+F</li> <li>• You can save the logs.</li> </ul>

Pane	Purpose	Use Case Scenario
<b>Breakpoints</b>	VuGen lets you include breakpoints in your Vuser scripts to help you to debug the scripts.  For details, see " <a href="#">Breakpoints Pane</a> " on page 135.	Enables you to set and manage breakpoints to help analyze the effects of the script on your application at pre-determined points during script execution.
<b>Watch</b>	The Watch pane enables you to monitor variables and expressions while a script runs, and is in the <b>Paused</b> state.  For details, see " <a href="#">Watch Pane</a> " on page 138.	
<b>Call Stack</b>	This debug pane enables you to view information about the methods and functions that are currently on the call stack of your script, or the context in which the run session was paused.  For details, see " <a href="#">Call Stack Pane</a> " on page 139.	

## VuGen Layouts - Overview


The VuGen window is composed of a number of zones. Each zone can contain a variety of panes, such as the Errors pane or the Snapshots pane. The panes appear as tabs within the zones. The figure below shows a zone that contains four tabbed panes: **Output**, **Tasks**, **Errors**, and **Run Time Data**. The **Output** pane is currently visible.



The specific configuration of the zones and the panes contained within the zones is called a layout. VuGen is supplied with a set of standard layouts: **Default**, **Debug**, **Plain**, **Record**, **Replay**, and **Snapshot**. Each layout is designed to enhance a specific phase of the Vuser script development process. For example, the Replay layout includes the panes that are most useful when you run a

Vuser script: **Errors**, **Call Stack**, **Watch**, **Breakpoints**, **Output**, and **Run Time Data**. VuGen automatically uses specific layouts during specific phases of the script development process. For example, the Record layout is used while you record a script, and the Replay layout is used when you replay a script.

The VuGen toolbar displays the layout that is currently used: **Debug layout**. To change the layout, click the **Layout** drop-down and select the required layout from the list of layouts, as shown below.



### Modifying a layout

You cannot add or delete a standard layout. However, you can modify most of VuGen's standard layouts to meet your specific requirements. When you modify a layout, you can add, move and resize zones, select which panes to include in each zone, and specify which of these panes is displayed by default. For task related details, see ["How to Modify the VuGen Layout" on page 93](#). After you modify a standard layout, VuGen maintains that layout until you change the layout again or reset the default layouts.

**Note:** VuGen does not save any changes that you make to the Plain layout.


### Restoring the layout defaults

On the VuGen toolbar, click the **Layout** drop-down, and select **Reset to Defaults**. VuGen resets all standard layouts to their default settings.

## Solution Explorer - Overview

The Solution Explorer enables you to easily organize and navigate through script entities, enhancing the recording, replay and debug process. You can create a solution containing multiple scripts of different protocols related to a full-cycle business process. Each script entity includes extra files (such as header files), run-time settings, parameters, and replay runs.

The following graphic illustrates the Solution Explorer structure:



## Solution

When you create a new script, you can name the solution that contains the script. For example, you can use the business process as the solution name. If you do not specify a name, the default name is "Untitled".

## Scripts

Your solution can contain multiple scripts. Single-click a script, or one of its assets, to change focus to that script. When a script in a solution is in focus, it changes the behavior of VuGen. For example, when you click replay, the script in focus runs. In addition, menus options, toolbars buttons, and panes display functionality relevant to the script's protocol. For example, the script in focus is recorded in Web HTTP/HTML , the **Recording Options** button is displayed on the toolbar. However, if the script in focus is recorded in TruClient, the **Develop Script** button is displayed on the toolbar.

Double-click the script's action to open it in the Editor.

In addition, you can drag and drop scripts (<scriptName>.usr) from the file directory to the **Solution Explorer**.

## Extra files

Additional files that are called by the script, are contained in the Extra Files node under **Solution Explorer > <ScriptName>**. You can drag and drop header files (<headerFileName.h>) from your file directory. When you include files in the Extra Files node, these files will automatically be included in a Load Generation Scenario.

The information contained in extra files can include:

- Common utility functions used by the script (for example, code)
- Definition of constants and variables used by the script (for example, code)
- Special assets used during script execution (such as .jpeg files)
- Data files manipulated by script code during script execution

The following are examples of file types that can be added as extra files:

.ws,.h,.c.,.dat,.ini,.vbs,.java,.js,.txt,.tux,.rec,.msc,.vdf,.xml,.xsl,.dtd,.html,.htm

You can edit extra files in the editor if the file type is included in **Tools > Options > Script Management > List of file types that can be edited in the Editor**. Double click the extra file to open it in the Editor. For details on how to modify the list, see "[Scripting Options](#)" on page 103.

## Run-time Settings

You can access run-time settings for a specific script from the Run-time Settings node in the **Solution Explorer > <Script> > Run-Time Settings**. For details, see "[Run-Time Settings](#)" on page 317.

## Parameters

You can access parameters for a specific script from the Parameters node in the **Solution Explorer > <Script> > Parameters**. For details, see "[Parameterizing - Overview](#)" on page 408.

## Replay Runs

This node enables you to access the **Replay Summary Reports** for each iteration in the replay. For details, see "[Solution Explorer Pane](#)" on page 118.

# Editor - Overview

VuGen's Editor enables you to edit recorded scripts and other supplementary files such as header files. You can open multiple files simultaneously, easily navigating tab by tab.

The Editor facilitates editing by providing the following features:

## Tab View

The tab view in the Editor allows you to organize and edit several script assets simultaneously. You can do the following in the Editor:

- Double-clicking on a script or extra files in the Solution Explorer will open the file in Editor area as a tab. The tab name is `<script name>:<filename>`
- Drag tabs to reorder them.

## Support of Multiple Programming Languages

Recorded scripts are generated in C, which has full language and parsing support in VuGen. You can enhance your Vuser scripts by adding standard ANSI C functions. ANSI C functions allow you

to add comments, control flow statements, conditional statements to your Vuser scripts. You can add standard ANSI C functions to any type of Vuser script. For details, see "[C Vuser Scripts](#)" on page 967.

In addition, the VuGen Editor enables you to write manual scripts with the following programming languages:

- Java

For details, see "[Java Vusers](#)" on page 968.

- C#

For details, see "[.NET Vusers](#)" on page 969.

- VB.NET

For details, see "[How to Create a Vuser Script in Visual Studio](#)" on page 970.

## Code Completion and Tooltips for C Scripts

Code completion enables you to quickly and accurately write code by providing a list of code items from which you can select. Press **CTRL + SPACE** to activate statement completion when your cursor is in the Editor. Tooltips, containing context information, appear when your mouse hovers over a code element. The following table describes available code completion items, scope, identifying icon, and tooltip context:

Code Completion Item	Scope	Icon	The Tooltip Displays
<b>ANSI C Keywords and Types</b>	All possible standard C keywords.		Function type, name, and parameters
<b>LR API Functions</b>	All steps in the script.		LR API Step
<b>LR API Constants</b>	Used to delimit groups of parameters in steps. For example, ENDITEM		LR API Constant
<b>User Functions</b>	All the functions that you have defined in action files.		<ul style="list-style-type: none"><li>• Function type, name and parameters.</li><li>• When Using Functions (Method Insight)</li></ul> <p>The required arguments, highlighting each argument as you define it moving to the next argument when you enter the delimiter.</p>

Code Completion Item	Scope	Icon	The Tooltip Displays
<b>Variables</b>	Local variables – visible only in the function where they have been defined.  Global variables – defined outside of any function body. Available everywhere in the script.		Type and name.
<b>Parameters</b>	Available only in the function body where they have been defined.		<ul style="list-style-type: none"> <li>Parameter type and name</li> <li>When Using parameters (Method Insight)</li> </ul> <p>The required arguments, highlighting each argument as you define it moving to the next argument when you enter the delimiter.</p>

By default, VuGen uses code completion globally. To disable code completion, select **Tools > Text Editor > Code Completion**. Clear the **Enable code completion** features check box.

## Script Code-Coloring for C Scripts

To facilitate script writing and debugging, code item types are colored by an identifying background and foreground. The colored text enables you to easily read scripts and scan for syntax errors. Below is a table that provides examples of code item types and their assigned colors.

Code Type	Color Example
Comments	<code>/* comment */ // comment</code>
Keywords	<code>if (a) { } else { }</code>
Method Parameter Name	<code>foo( "parameter=value" )</code>
LoadRunner API	<code>web_url</code>
Method Call	<code>foo()</code>
String	<code>char * text = "Hello, World!"</code>

In addition, you can customize code item types to suit your needs by selecting **Tools > Options > Text Editor > Highlighting**.

## Script Folding for C Scripts

Script folding enables you to selectively hide and display sections of a script, making it easier to manage large scripts by viewing only those sections that you are currently editing. For details, see "[Editor Options](#)" on page 98.

## Community Search

You can perform Web searches from the VuGen toolbar, which opens a browser tab in the Editor. The default Web site is the LoadRunner Forum which enables you to search topics, post questions, or blog about your expertise. You can add additional search sites by selecting **Tools > Options > General > Community**. For details on adding additional sites, see "[General Options](#)" on page 95.

## Snapshot Pane - Overview

What is a snapshot?

Snapshots contain the data generated by the traffic between the client and the server and are captured when a script is recorded and when the script is replayed.

Snapshots are displayed in various formats and provide different functionality depending on the Vuser protocol:

Type	Description	Snapshot functionality
Windows Sockets	Textual and hexadecimal representations of data buffers sent and received.	Create correlation
Web HTTP/HTML	Textual and hexadecimal representations of the request and response.	<ul style="list-style-type: none"><li>• Create correlation</li><li>• Create correlation rule</li><li>• Create Parameter</li><li>• Add text check step</li></ul>
XML	XML, textual and hexadecimal representation of the request and response bodies.	<ul style="list-style-type: none"><li>• Insert correlation</li><li>• Create correlation rule</li><li>• Create Parameter</li><li>• Insert XML check</li></ul>

Type	Description	Snapshot functionality
Database	Data grid	<ul style="list-style-type: none"><li>• Create correlation</li><li>• Save grid to file</li></ul>
Image based protocols such as Click & Script	Graphic images of the step.	

**Note:** The Snapshot pane is not available for all Vuser protocols - only specific Vuser protocols give you access to the Snapshot pane.

### The Snapshot Pane

VuGen displays record and replay snapshots in the Snapshot pane. By default, the Snapshot pane shows just a single snapshot. To enable you to compare snapshots, you can split the Snapshot pane to show two snapshots simultaneously. You can split the Snapshot pane either vertically or horizontally. Each section of the split Snapshot pane can show either a record snapshot or a replay snapshot. Typically, you would show a record snapshot together with its corresponding replay snapshot. This enables you to compare the record snapshot with the replay snapshot.

- For details on working with the Snapshot pane, see ["How to Work with Snapshots" on page 88](#).
- For details on the Snapshot pane user interface, see ["Snapshot Pane" on page 126](#).

### Basic Snapshot pane functionality

The Snapshot pane that is displayed for all Vuser protocols includes the same basic functionality. This basic functionality includes the ability to:

- Show one snapshot, or split the Snapshot pane to show two snapshots. You can split the Snapshot pane either horizontally or vertically.
- Show record and replay snapshots.

For details on how to use the basic Snapshot pane functionality, see ["How to Work with Snapshots" on page 88](#).

### Synchronizing snapshots

The Snapshot pane that is displayed for some Vuser protocols improves your ability to compare snapshots by “synchronizing” the two snapshots that are displayed in the Snapshot pane. For example, when synchronizing graphic snapshots, if you place the mouse cursor over a specific location in one of the snapshots, VuGen displays a marker at the corresponding location in the other snapshot. In addition, as you move one snapshot vertically or horizontally within the Snapshot pane, VuGen moves the other snapshot accordingly, ensuring that the same section of each snapshot is displayed.

**Note:** Snapshot synchronization is available for only specific Vuser protocols, and for only specific views within these protocols.

## Copying snapshots to the clipboard

You can copy an image-based snapshot to the clipboard. This enables you to import the image into a graphics application, where you can analyze and modify the graphic.

For details on how to copy a snapshot to the clipboard, see "[How to Work with Snapshots](#)" on the [next page](#).

**Note:** The "copy snapshot to the clipboard" functionality is available for only RDP, Citrix, and SAP GUI protocols.

## Copying snapshot text to the clipboard

You can copy text from a snapshot to the clipboard. You can then paste the text from the clipboard into another application.

For details on how to copy snapshot text to the clipboard, see "[How to Work with Snapshots](#)" on the [next page](#).

**Note:** The "copy snapshot text to the clipboard" functionality is available for only Ajax - Click & Script and SAP - Click & Script protocols.

## Customized Snapshot pane functionality

In addition to the basic Snapshot pane functionality, the Snapshot panes for some Vuser protocols include customized functionality. For example, the Snapshot pane for RDP Vuser scripts lets you display snapshots in either **Full** or **Image** modes; the Snapshot pane for Winsock Vuser scripts lets you display snapshots in either **Text** or **Hex** modes. The controls for the customized functionality can be found in the Snapshot pane toolbars.

## Snapshot on error

In addition to showing record and replay snapshots, the Snapshot pane can display snapshots of errors that occurred during the replay of a script. The "snapshot on error" functionality is available for only specific Vuser protocols.

You can generate and display snapshots of errors only if the "snapshot on error" functionality is activated. For details on how to activate the snapshot-on-error functionality, see "[How to Work with Snapshots](#)" on the [next page](#).

## Comparing snapshots

The **Compare** button in the Snapshot pane enables you to compare two snapshots. To enable the **Compare** functionality, you must first split the Snapshot pane to show two snapshots. By default, VuGen uses the *WDiff* utility to compare snapshots. You can specify an alternative comparison tool as described in "[Scripting Options](#)" on page 103.

**Note:** The snapshot comparison functionality is available for only the Web (HTTP/HTML) and Web Services protocols.

## Setting snapshot options

VuGen allows you to set various options that define how snapshots are displayed in the Snapshot pane. For details on these snapshot options, see "[Scripting Options](#)" on page 103.

# How to Work with Snapshots

This topic describes how to use the basic Snapshot pane functionality. For an overview of the snapshot functionality, see "[Snapshot Pane - Overview](#)" on page 85.

## How to show the Snapshot pane

To show the Snapshot pane, do one of the following options:

- Select **View > Snapshot**.
- Click the **Snapshot** button  on the VuGen toolbar.
- In the Editor, click inside a step that contains a reference to a snapshot.
- In the Step Navigator, double-click a step that contains a reference to a snapshot. Note that in the Step Navigator, each step that contains a snapshot displays a Snapshot icon . You can place your mouse cursor over the snapshot icon to see a thumbnail view of the snapshot.



## How to show a record snapshot in the Snapshot pane

Click the **Recording Snapshot** button



on the Snapshot pane toolbar.

## How to show a replay snapshot in the Snapshot pane

Click the **Replay Snapshot** button on the Snapshot pane toolbar. If more than one replay snapshot exists for the step, click **Iteration** and select the required iteration number.

## How to split the Snapshot pane to show two snapshots

If the Snapshot pane displays only one snapshot, click the **Split Snapshot Pane** button on the Snapshot pane toolbar.

## How to show only one snapshot in the Snapshot pane

If the Snapshot pane displays two snapshots, click the **Single** button on the Snapshot pane toolbar.

## How to toggle between a horizontal split and a vertical split of the Snapshot pane

If the Snapshot pane displays two snapshots:

- Click the **Horizontal Split** button on the Snapshot pane toolbar to show two snapshots side-by-side.
- Click the **Vertical Split** button on the Snapshot pane toolbar to show two snapshots, one above the other.

## How to synchronize the display of two snapshots when the Snapshot pane is split

1. Make sure that the Snapshot pane is split to show two snapshots.

2. On the Snapshot pane toolbar, click the Synchronization button .

**Note:** Snapshot synchronization is available for only specific Vuser protocols, and for only specific views within these protocols.

## How to copy a snapshot to the clipboard

1. Display the snapshot in the Snapshot pane.

2. Right-click on the snapshot, and then select **Copy Image to the Clipboard**.

**Note:** The "copy snapshot to the clipboard" functionality is available for only RDP, Citrix, and SAP Vuser scripts.

## How to copy snapshot text to the clipboard

1. Display the snapshot in the Snapshot pane.
2. Select the text that you want to copy.
3. Right-click in the selected text, and select **Copy Selection**.

## How to activate the snapshot-on-error functionality

1. Click **Replay > Run-Time Settings**. The Run-Time Settings dialog box opens.
2. Under **General**, click **Miscellaneous**.
3. Under **Error Handling**, select the **Generate snapshot on error** check box.

## How to set the snapshot options

1. Click **Tools > Options**. The Options dialog box opens.
2. Click **Scripting**, and then click **Snapshot**. The snapshot options appear on the right of the dialog box.

## How to Add a Text Check From the XML View in the Snapshot Pane

After recording a Vuser script, you can add a text check from the XML view in the Snapshot pane. For details on the XML view in the Snapshot pane, see Snapshots That Have an XML View.

To add a text check from the XML view in the Snapshot pane:

1. Click **View > Snapshot**, or click the **Show Snapshot Pane** button  on the VuGen toolbar.
2. In the Snapshot pane, display a snapshot that contains the text that you want to verify.
3. On the right-side of the Snapshot pane, click the **XML View** tab.
4. In the Snapshot pane, click the **Response Body** tab.
5. In either the Tree view or the Grid view, locate and select the text string that you want to verify.
6. Right-click inside the selection, and select **Add Text Check Step**. The Find Text dialog box opens.
7. Modify the options in the Find Text dialog box. For details on the dialog box options, press F1 when in the dialog box to open the Function Reference.
8. Click **OK** to insert a **web\_reg\_find** step into the Vuser script.

## How to Create a Vuser Script - Workflow

The following diagram outlines the process of developing a Vuser script:



The process of creating a Vuser script is as follows:

1. Record a basic script using VuGen.
2. Enhance the basic script by adding control-flow statements and other LoadRunner API functions into the script.
3. Configure the run-time settings. These settings include iteration, log, and timing information, and define the Vuser behavior during a script run.
4. Verify the script's functionality, by running it in standalone mode.
5. After you verify that the script is functional, you integrate it into your environment: a LoadRunner scenario, Performance Center load test, or Business Process Monitor profile.

## How to Compare Scripts Side by Side

Vuser scripts can be compared and displayed side by side using the comparison tool.

### To compare Vuser scripts

1. Right click on the primary script in **Solution Explorer** and select **Set as first comparing object**.
2. Right click on the secondary script in the **Solution Explorer** and select **Compare** which will run the compare functionality.

or
3. Right click and select **Compare with external object**.

You can compare an asset to a file outside of the solution. This option sets the highlighted asset as the primary asset and opens Windows Explorer to enable you to select the secondary asset.

**Note:** You can change the comparison tool from **Options > Scripting > Comparison**. For more information, see "[Scripting Options](#)" on page 103.

## How to Create a Business Process Report

At the final stage of script creation, you can create a report that describes your business process. VuGen exports the script information to one of the following formats:

- Microsoft Word
- Acrobat PDF
- HTML

You can use a pre-designed template or one provided with VuGen, to create reports with summary information about your test run. The VuGen template is available in Microsoft Word 2007 (docx) format. You can edit or update the template according to your requirements.

VuGen lets you customize the contents of the report by indicating what type of information you want to include.

**Note:** Business Process Reports are available for the following protocols: Ajax (Click & Script), TruClient, Citrix ICA, Oracle NCA, Oracle Web Applications 11i, RDP, SAP (Click & Script), SAP GUI, SAP - Web, Web (HTTP/HTML), and Web Services.

### 1. Create a business process report

Select **Tools > Create Business Process Report** and complete the dialog box. For user interface details, see "[Business Process Report Dialog Box](#)" on page 115.

### 2. Configure additional options

To modify additional report options such as the table of contents, snapshots, and the document template, click the **More** button. For user interface details, see "[Business Process Report](#)

[Dialog Box" on page 115.](#)

## How to Modify the VuGen Layout


The VuGen window is composed of a number of zones. Each zone can contain a variety of panes, such as the Errors pane and the Snapshot pane. When more than one pane is included in a zone, the panes appear as tabs within the zone. This section describes how to customize and modify the zones and panes that appear in the VuGen window.

### Moving a pane to a new zone

You can move any VuGen pane to a new zone. The new zone can be either a portion of an existing zone, or it can occupy the entire left, right, top, or bottom of the VuGen window.

In the VuGen window, drag the title bar or tab of the pane that you want to move. (If the required pane is not displayed in the VuGen window, you can select it from the **View** menu.) As you drag the pane over the zones in the VuGen window, a complex marker is displayed in the center of the active zone and a simple marker appears on each edge of the VuGen window.


**Note:** If you drag the title bar of a zone that contains multiple tabbed panes, then all the panes in the zone are moved to the new zone.

Marker Type	Marker	Description
<b>Complex marker - Current zone</b>		Positions the selected pane in a new zone. The new zone is created in the top, bottom, left, or right of the <b>active zone</b> , according to the arrow marker selected when you release the mouse button.
<b>Simple marker - VuGen window</b>		Positions the selected pane in a new zone. The new zone is created in the top, bottom, left, or right of the <b>VuGen window</b> , according to the arrow marker selected when you release the mouse button.

### Moving a pane to an existing zone

You can move any VuGen pane from one zone to another. When more than one pane is included in a zone, the panes appear as tabs within the zone.

1. In the VuGen window, drag the title bar or tab of the pane you want to move. (If the required pane is not displayed in the VuGen window, you can select it from the View menu). As you drag the pane over the zones in the VuGen window, a complex marker is displayed in the center of the active zone.



2. Locate the cursor over the center button of the complex marker. When you release the mouse button, the selected pane is added as a tabbed pane to the selected zone.
3. Repeat this procedure for each pane you want to move.

**Note:** If you drag the title bar of a zone that contains multiple tabbed panes, then all the panes in the zone are moved to the selected zone.

## Floating and docking panes

Docked panes are fixed in a set position within the VuGen window. For example, when you move a pane to a position indicated by a marker, the pane is docked in that position.

Floating panes are displayed on top of all other windows. Floating panes can be dragged to any position on your screen, even outside the VuGen window. Floating panes have their own title bars.

- To float a pane, right-click the title bar, and click **Float**. The pane opens on top of all the other windows and panes, with its own title bar.
- To dock a pane, double-click the title bar, or right-click the title bar and select **Dock as tabbed document**. The pane returns to its previous position in the VuGen window.

# Options Overview

The **Options** dialog box is comprised of VuGen application settings. The settings are common to all protocols available in VuGen.

Specific details of each of the settings are described in the topic of the relevant category topic.

The following table includes a list of the categories and related sections from the **Options** dialog box.

<b>General</b>	<ul style="list-style-type: none"><li>• <b>Task List</b> enables you to add, update and delete comment tags.</li><li>• <b>Projects and Solutions</b> enables you to configure project settings.</li><li>• <b>Community</b> enables you to add, update and delete Community Search Sites.</li></ul> <p>For details, see "<a href="#">General Options</a>" on the next page.</p>
----------------	--

Editor	<ul style="list-style-type: none"><li>• <b>General</b> enables you to configure font and other general options.</li><li>• <b>Markers and Rulers</b> enables you to configure markers and rulers for text used in a script.</li><li>• <b>Behavior</b> enables you to configure settings related to tabs, keystrokes and mouse behavior.</li><li>• <b>Code Color</b> enables you to configure the font settings for each heading, control and text type for each language type.</li><li>• <b>Code Completion</b> enables you to configure the settings for code completion.</li></ul> <p>For details, see "<a href="#">Editor Options</a>" on page 98.</p>
Scripting	<ul style="list-style-type: none"><li>• <b>Recording UI</b> enables you to configure the settings related to the recording user interface, for example the floating toolbar used when recording.</li><li>• <b>Replay</b> enables you to configure the settings related to replay of the script.</li><li>• <b>Script Management</b> enables you to edit the list of file extensions.</li><li>• <b>Comparison</b> enables you to enter the location of the comparing application.</li><li>• <b>Step Navigator</b> enables you to select the background and foreground colors for the <b>Step Navigator</b> pane.</li><li>• <b>Thumbnails</b> enables you to configure the <b>Thumbnail Explorer</b>.</li><li>• <b>Output Pane</b> enables you to configure the appearance of the <b>Output Pane</b>.</li><li>• <b>Snapshot</b> enables you to configure appearance of snapshots in your script.</li><li>• <b>Parameters</b> enables you to define the delimiter to use for parameter braces throughout a script.</li><li>• <b>Parser</b> enables C language parser.</li></ul> <p>For details, see "<a href="#">Scripting Options</a>" on page 103.</p>

## General Options

This pane enables you to configure general user interface options.

### Task List

To access	<b>VuGen &gt; Tools &gt; Options &gt; General &gt; Task List</b>
-----------	--

User interface elements are described below:

UI Element	Description
Comment Tags	<p>This pane enables you to add, delete or modify tags names that you can use to label comment tasks in your scripts.</p> <p><b>Tags.</b> List of available tags.</p> <p><b>Name.</b> Displays the name of the highlighted tags in the token list. This area enables you to modify, add or delete the current tag.</p> <p><b>Add.</b> Enables you to add a tag to the token list.</p> <p><b>Edit.</b> Enables you to modify the name of tag from the token list.</p> <p><b>Delete.</b> Enables you to delete a tag from the token list.</p>

## Scripts and Solutions

To access	VuGen > Tools > Options > General > Scripts and Solutions
-----------	---

User interface elements are described below:

UI Element	Description
Settings	<p><b>Default project location</b></p> <p>Enables you to specify a path to your saved projects. Default location = C:\Users\&lt;username&gt;\Documents\SharpDevelop Projects</p> <p><b>Load previous solution on startup</b></p> <p>Enables you to automatically load the previous solution.</p> <p>By default this option is enabled.</p>
Start Page Settings	<p><b>Display Start Page on startup</b></p> <p>By default this option is enabled.</p> <p><b>Close Start Page after script loads</b></p> <p>By default this option is enabled.</p>

## ALM

To access	VuGen > Tools > Options > General > ALM
-----------	---

User interface elements are described below:

UI Element	Description
<b>Connect to ALM in CAC mode</b>	Connects to HP Application Lifecycle Management using CAC (Common Access Card). This enables you to log in without providing a username and password.

## Community

To access	<b>VuGen &gt; Tools &gt; Options &gt; General &gt; Community</b>
See also	For details, see Community Search in the " <a href="#">Editor - Overview</a> " on page 82.

User interface elements are described below:

UI Element	Description
<b>Community Search Sites</b>	
	<p>Adds a new search site to the list of Community search sites.</p> <ul style="list-style-type: none"><li><b>Name:</b> Enables you to specify a name of the search site that is displayed on the VuGen toolbar.</li><li><b>URL:</b> Enables you to specify the URL of the search site.</li></ul> <div style="background-color: #f0f0f0; padding: 5px;"><p>Example URLs</p><p>http://www.bing.com/search?q=%QUERY%</p><p>http://www.google.com/search?q=%QUERY%</p><p>http://www.google.de/search?q=%QUERY% (localized google site, e.g. de for Germany)</p><p>http://en.wikipedia.org/wiki/%QUERY%</p></div>
	Enables you to edit the properties of the custom search site.
	Deletes the search site from the list of available sites.
	Moves the search site lower down on the list of available sites.
	Moves the search site higher up on the list of available sites.


## ***Editor Options***

This pane enables you to configure the text editor options.

### **General**

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Editor &gt; General</b>
------------------	---


User interface elements are described below:

UI Element	Description
<b>Font</b>	
<b>Text Font</b>	Enables you to select the font.
<b>Size</b>	Enables you to select the font size.
<b>General Options</b>	
<b>Word wrap</b>	Automatically wraps text to the next line.  By default this option is disabled.
<b>Show Class/Function Browser</b>	Show or hide the Class/Function Browser. When enabled, you can navigate quickly to a specific class or function in your script by selecting it from the drop-down list in the browser.  By default this option is enabled.
<b>Show line numbers</b>	Enable line numbering of script in the Editor.  By default this option is enabled.
<b>Check for line ending inconsistencies</b>	Enable the editor to check for end of line inconsistencies in your script. If enabled, a utility appears in the script editor that enables you to normalize line endings based either on a Windows standard (CRLF) or a Linux standard (LF).    This option is enabled by default.
<b>Enable working URL hypertext links in the Editor</b>	Enable URLs in scripts to function as hypertext links. Disabling this option may increase performance.  By default this option is enabled.

## Markers and Rulers

To access	VuGen > Tools > Options > Editor > Markers and Rulers
-----------	---

User interface elements are described below:

UI Element	Description
<b>Markers and Rulers</b>	
Show spaces	Enable markers that indicate where tabs exists. By default this option is disabled.
Show tabs	Enable markers that indicate where line ends. By default this option is disabled.
Show end-of-line makers	Enable markers that indicate where line ends. By default this option is disabled.
Underline errors	Enable underlining of errors. By default this option is enabled.
Highlight matching brackets	Enable highlighting of matching brackets. By default this option is enabled.
Highlight symbols	When this option is enabled, you can select a non-keyword in your script and the Editor will highlight all other occurrences in your script.  By default this option is enabled.

## Behavior

To access	VuGen > Tools > Options > Editor > Behavior
-----------	---

User interface elements are described below:

UI Element	Description
<b>Tabs</b>	
<b>Indentation</b>	Enables you to set the spacing for tab indentation.  Default indentation is four spaces.
<b>Convert tabs to spaces</b>	Converts tabs to spaces.  By default this option is disabled.
<b>Use smart indentation</b>	Automatically applies the indentation format from the previous line.  By default this option is enabled.
<b>Behavior</b>	
<b>Enable zoom with mouse wheel</b>	Enables you to use the mouse wheel to zoom.  By default this option is enabled.
<b>Cut or Copy entire line when nothing is selected</b>	Allows you to cut or copy an entire line without highlighting it in the editor, as long as the cursor is within that line.  By default this option is enabled.
<b>Enable Ctrl + Click for "Go to Definition"</b>	Enables the Ctrl + Click shortcut for "Go To Definition". This lets you move the cursor to the definition of a function you highlighted in the editor.  By default this option is enabled.

## Code Color

To access	VuGen > Tools > Options > Editor > Highlighting
Important information	Highlighting options enable you to customize the color of script elements.

User interface elements are described below:


UI Element	Description
------------	-------------

<b>&lt;Language Selection&gt;</b>	Drop-down list of script languages for which you can customize appearance including: <ul style="list-style-type: none"><li>• C#</li><li>• HTML</li><li>• VuGen C</li><li>• XML</li></ul>
<b>&lt;Element Selection&gt;</b>	List of code elements whose appearance you can customize.
<b>Foreground color</b>	Enables you to select a color from the pallet. The select color is applied to the foreground of the code element.
<b>Background color</b>	Enables you to select a color from the pallet. The select color is applied to background of the code element.

## Code Completion

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Editor &gt; Code Completion</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Enable code completion features</b>	Code completion features are enabled. For details on code completion, see " <a href="#">Editor - Overview</a> " on page 82.  By default this option is enabled.
<b>Enable syntax tooltip</b>	Enables tooltips that display function arguments. Each argument is highlighted as you are defining it, moving to the subsequent argument when the delimiter is entered.    By default this option is enabled.

<b>Show tooltips when mouse pointer stops over an identifier</b>	When this option is enabled, a description of the code elements is displayed when the mouse hovers over the identifier. This option is disabled when <b>Show tooltips in debug mode only</b> is enabled.  By default this option is enabled.
<b>Show tooltips in debug mode only</b>	Tooltips are displayed in debug mode only.  By default this option is disabled.
<b>Include in the code completion list</b>	
<b>ANSI C keywords</b>	Enables you to include ANSI C keywords in code completion list.  By default this option is enabled.
<b>LoadRunner API Steps</b>	Enables you to include LoadRunner API Steps in the code completion list.  By default this option is enabled.
<b>LoadRunner API Constants</b>	Enables you to include LoadRunner API Constants in the code completion list.  By default this option is disabled.
<b>User-defined functions</b>	Enables you to include user-defined functions in the code completion list.  By default this option is enabled.
<b>Function parameters, local and global variables</b>	Enables you to include function parameters, local, and global variables in the code completion list.  By default this option is enabled.

## Folding

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Editor&gt; Folding</b>
------------------	--

User interface elements are described below:

UI Element	Description
<b>Enable folding features</b>	This option enables expanding and collapsing of script sections.  By default this option is enabled.
<b>Enable steps folding</b>	This option enables expanding and collapsing of script steps.  By default this option is disabled.

<b>When step length is more than [ ] characters</b>	Enables you define the number of characters in a step before implementing folding.  By default this option is disabled.
<b>When step consists of more than [ ] lines</b>	Enables you to define the number of lines to a step before implementing folding.  By default this option is disabled.

## ***Scripting Options***

This pane enables you to configure options related to recording, replaying and debugging scripts.

### **Recording UI**

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Recording UI</b>
------------------	---

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Enable Recording Floating Toolbar transparency mode</b>	Display a transparent floating recording toolbar. When you click or hover on the toolbar it becomes opaque.  By default this option is disabled.
<b>Enable 'Cancel Recording' button</b>	Enable the <b>Cancel Recording</b> button on the floating recording toolbar.  <b>Note:</b> When the <b>Cancel Recording</b> button is enabled, there may be a delay when you start recording into an existing script. This delay occurs while VuGen makes a copy of the existing script.  By default, this option is enabled.
<b>Open Start Recording Dialog Box after new script is created</b>	Automatically open the Start Recording Dialog Box after a new script is created.  By default this option is disabled.
<b>Automatically close transactions</b>	Enable this function if you want VuGen to insert an end transaction step for open transactions before recording a subsequent action.  By default this option is disabled.

### **Replay**

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Replay</b>
------------------	---

User interface elements are described below:

UI Element	Description
Layout	<p><b>Do not switch the layout during Replay.</b> By default, when you replay a script, VuGen automatically switches the UI layout to the <b>Debug</b> layout. This option enables you to maintain your selected layout during replay.</p> <p>By default this option is disabled.</p>
Animated Run	<p><b>Animated Run</b></p> <p>You can run a Vuser script in animated mode or non-animated mode. When you run in animated mode, VuGen highlights the line that is running in the Vuser script. When you run in non-animated mode, VuGen executes the Vuser script, but does not indicate the line being executed.</p> <p>By default this option is enabled.</p> <p><b>Animated Run Delay</b></p> <p>You can set a delay of the highlighting in the animated run, allowing you to better view the effects of each step. You set the delay in milliseconds.</p> <p>The default delay is 1.</p> <p><b>Animate Functions in the Action section only</b></p> <p>Animates the content of the Action sections only, not the init or end sections.</p> <p>By default this option is enabled.</p>
Results	<p><b>Enable result of replay summary to be saved to a named folder after each script run</b></p> <p>When this option is enabled the dialog box prompts you to name a results file before running a script in VuGen. When not enabled, VuGen automatically names the directory 'result1'. Subsequent script runs will automatically overwrite previous results files unless you specify a different name.</p> <p><b>Note:</b> Results are stored in a subdirectory of the script.</p> <p>By default this option is disabled.</p> <p><b>Generate report during script execution</b></p> <p>By default this option is disabled.</p>

<b>During Replay</b>	<ul style="list-style-type: none"><li><b>Show run-time view during replay</b> Enables the run-time viewer</li><li><b>Auto Arrange Window</b> Select this option to arrange the two viewers side by side. This option is disabled by default.</li><li><b>Collect replay statistics</b> Select this option to enable the collection of replay-time statistics. The data collected is displayed in the Replay Summary report. This option is enabled by default. For details, see "<a href="#">Replay Summary Tab</a>" on page 140</li></ul>
<b>After replay</b>	<p><b>After replay show</b> Instructs VuGen how to proceed after the replay:</p> <ul style="list-style-type: none"><li><b>Script.</b> Show script in the Editor.</li><li><b>Replay summary.</b> Go directly to the Replay Summary window in the Editor. (Default)</li></ul>

## Script Management

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Script Management</b>
------------------	--

User interface elements are described below:

UI Element	Description
<b>List of file types, by extension, that can be edited in the Editor</b>	Enables you to modify the list of valid file extensions that can be edited in the Editor.

## Comparison

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Comparison</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Path to comparing tool</b>	You can select a comparison tool to be used when comparing two scripts. VuGen is installed with a default comparison tool (Wdiff).  Click the browse button to locate a third-party comparison tool that is installed on your local machine.

<b>Command line arguments</b>	This option contains the mandatory default arguments %1 and %2 for the two files you want to compare, which should not be modified. You can add additional arguments, as needed, for your comparison tool.
-------------------------------	--

## Step Navigator

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Step Navigator</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Enable Editor highlighting</b>	This option enables you to highlight filtered steps in your script.
<b>Background color</b>	Enables you to select a background color to apply to the filtered steps in your script.
<b>Border color</b>	Enables you to select a border color to apply to the filtered steps in your script.

## Thumbnails

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Thumbnails</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Enable Thumbnail Explorer</b>	Enables slide view of generated thumbnails in the Thumbnail Explorer. Double clicking a thumbnail sets the cursor at the associated step in the script.
<b>Highlight the thumbnail associated with a step</b>	Sync the display of the Thumbnail Explorer while scrolling through steps in the Editor.
<b>Show important thumbnails by default</b>	VuGen displays thumbnails directly related to the business process and filters out less important thumbnails by default.
<b>Enable Automatic Creation</b>	Enables the automatic creation of thumbnails during the application's idle time.
<b>Cache thumbnails to script folder</b>	Optimize VuGen's performance by saving rendered thumbnails to a cache file. Thumbnails are loaded from the cache file after the initial generation.

## Output Pane

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Output</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Format</b>	<b>Word wrap</b>  Enables word wrapping in Output pane.
<b>Font</b>	<b>Text Font</b>  Enables you to select a font.  <b>Size</b>  Enables you to select a font size.

## Java

To access	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Java</b>
-----------	---

User interface elements are described below:

UI Element	Description
<b>Eclipse IDE Location</b>	<b>Browse</b>  Enables you to set the location of the Eclipse program, <b>eclipse.exe</b> .

## Citrix

To access	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Citrix</b>
-----------	---

User interface elements are described below:

UI Element	Description
<b>Show client during replay</b>	Shows the Citrix client during script replay.
<b>Show Bitmap Selection popup</b>	Issues a popup message when inserting a Get Text or Sync Bitmap function before selecting a bitmap or text in the snapshot.

## Snapshots

To access	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Snapshots</b>
-----------	--

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Enable snapshot viewing</b>	Enables the viewing of snapshots when you click on a step in the editor or step navigator. This option allows you to improve VuGen's performance when working with very large scripts.
<b>Enable enhanced XML view</b>	<p>Enables the following XML viewer visual features:</p> <ul style="list-style-type: none"> <li>• XML tree</li> <li>• coloring</li> </ul> <p>Clear this option to reduce the amount of memory consumed by the XML view.</p>
<b>Enable snapshot caching</b>	<p>Allows snapshots to be cached.</p> <p>Clear this option where you are working with large snapshots and are running out of memory.</p>
<b>Do not load text snapshots larger than</b>	Text-based snapshots are not loaded if they are larger than the specified size.
<b>Do not load binary snapshots larger than</b>	Binary [hexadecimal] based snapshots are not loaded if they are larger than the specified size.
<b>Do not load XML snapshots larger than</b>	XML-based snapshots are not loaded if they are larger than the specified size.

## Parameters

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Parameters</b>
------------------	---

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Left parameter delimiter</b>	<p>Enables you to specify a left parameter delimiter.</p> <p>The following characters are valid: !, #, \$, %, &amp;, (, ), [ , ], { , },  , ~, ` , &lt;, &gt;, ?</p> <p><b>Note:</b> If you change the left parameter delimiter, the specified delimiter will be applied to new Vuser scripts only, not to existing scripts.</p>

<b>Right parameter delimiter</b>	Enables you to specify a right parameter delimiter.  The following characters are valid: !, #, \$, %, &, (, ), [ , ], { , },  , ~, ` , < , > , ?  <b>Note:</b> If you change the right parameter delimiter, the specified delimiter will be applied to new Vuser scripts only, not to existing scripts.
<b>Parameter background color</b>	Enables you to specify the background color for parameters in a Vuser script.
<b>Parameter border color</b>	Enables you to specify the border color for parameters in a Vuser script.
<b>Restore Delimiter Defaults</b>	Resets both the left and right parameter delimiters to their default values.

## Parser

<b>To access</b>	<b>VuGen &gt; Tools &gt; Options &gt; Scripting &gt; Parser</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Enable C Language Parser</b>	Disabling the C language parser may improve application performance when you are working with very large scripts. However, the following features will be disabled: <ul style="list-style-type: none"><li>• Editing step arguments in the <b>Editor</b></li><li>• Statement completion</li><li>• Snapshots</li><li>• Tasks</li><li>• Thumbnails</li><li>• Additional step-related functionality</li></ul> This option is enabled by default.

## Search and Replace Dialog Boxes

These dialog boxes enable you to find and replace text strings in Vuser scripts and solutions.

## Search Dialog Box

To access	<ul style="list-style-type: none"><li>• VuGen &gt; Search &gt; Quick Find</li><li>• VuGen &gt; Search &gt; Find in Files</li></ul>
Note	Some of the UI elements in the table below appear in the <b>Quick Find</b> dialog box only and some appear in the <b>Find in Files</b> dialog box only.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Search-type dropdown>	Enables you to specify the type of search to perform: <b>Quick Find</b> or <b>Find in Files</b> . Note that the UI of the Search dialog box changes depending on the selection.
Find text	Specify the text to search for.
	Shows the Regular Expression Builder. The Regular Expression Builder enables you to build a regular expression in the <b>Find text</b> box.
Regular Expression	Select <b>Regular Expression</b> to indicate that the <b>Find text</b> string is a regular expression.
Scope	Specify the files in which to search.
Match case	Distinguishes between uppercase and lowercase characters during the search.
Match whole word	Searches for occurrences that are whole words, and not part of a larger word.
Search up	Performs the searches upwards.
Include in search	Enables you to select which entities are included in the search.
Directory	Specify the folder that contains the files that will be searched during a "Find in Files" search.
Options	Enables you to specify options when performing a "Find in Files" search.
Find Next	Finds the next occurrence of the text or regular expression in the <b>Find text</b> box.

<b>Find All</b>	Finds all occurrences of the text or regular expression that appears in the <b>Find text</b> box. The results appear in the Search Results pane. In the Search Results pane, you can: <ul style="list-style-type: none"><li>Right-click an entry and select <b>Locate</b> to show the corresponding text in the Vuser script or wherever it is located.</li><li>Right-click an entry and select <b>Copy</b> to copy the selected search result to the clipboard.</li><li>Right-click and select <b>Copy All</b> to copy all the search results to the clipboard.</li></ul>
-----------------	--

## Replace Dialog Box

<b>To access</b>	<b>VuGen &gt; Search &gt; Quick Replace</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Find text</b>	Specify the text to search for.
	Shows the Regular Expression Builder. The Regular Expression Builder enables you to build a regular expression in the <b>Find text</b> box.
<b>Regular Expression</b>	Select <b>Regular Expression</b> to indicate that the <b>Find text</b> string is a regular expression.
<b>Replace with</b>	Specify the text that will replace the <b>Find text</b> .
<b>Scope</b>	Specify the files in which to search.
<b>Options</b>	Enables you to specify options when performing the search.
<b>Match case</b>	Distinguishes between uppercase and lowercase characters during the search.
<b>Match whole word</b>	Searches for occurrences that are whole words, and not part of a larger word.
<b>Search up</b>	Performs the searches upwards.
<b>Find Next</b>	Finds the next occurrence of the text or regular expression in the <b>Find text</b> box.
<b>Replace</b>	Replaces the selected text with the text in the <b>Replace with</b> box.
<b>Replace All</b>	Replaces all found occurrences of the text or regular expression in the <b>Find text</b> box with the text in the <b>Replace with</b> box.

## Editor

This pane enables you to edit scripts and other related script files. In addition you can open a browser session to search sites, such as the LoadRunner Forum.

<b>To access</b>	The Editor is opened when VuGen is loaded.
<b>Important information</b>	<ul style="list-style-type: none"><li>The Editor is automatically displayed as part of the default layout.</li><li>Press <b>Ctrl + Tab</b> to display a list of tabs and panes. Highlight and click to switch tabs in the Editor.</li><li>Press <b>Ctrl + g</b> or select <b>Search &gt; Go to...</b> to go to a specific line in the script.</li><li>Other main interface panes such as Output, Error, and Snapshot synchronize their displays based on your location in the Editor.</li><li>You can double-click an asset in the Solution Explorer to open it in the Editor.</li><li>Script modifications are displayed as highlighted text in the editor. The following are examples:<ul style="list-style-type: none"><li>Script has been modified but not saved.</li><li>Script has been modified and saved.</li><li>Breakpoint has been inserted.</li></ul></li></ul>
<b>See Also</b>	<ul style="list-style-type: none"><li><a href="#">"Editor - Overview" on page 82</a></li><li><a href="#">"Editor Options" on page 98</a></li></ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Gutter>	<p>The Editor gutter enables you to add toggle functionality including:</p> <ul style="list-style-type: none"><li>Breakpoints<ul style="list-style-type: none"><li>For details, see <a href="#">"Working with Breakpoints" on page 392</a> or <a href="#">"Breakpoints Pane" on page 135</a>.</li></ul></li><li>Bookmarks<ul style="list-style-type: none"><li>For details, see <a href="#">"How to Use Bookmarks" on page 385</a>.</li></ul></li></ul>
<b>Class/Function Browser</b>	When enabled, you can navigate quickly to a specific class or function in your script by selecting it from the drop-down list in the browser.

UI Element	Description										
<b>Line numbers</b>	Display of line numbers in the script.										
<b>Context Menu</b>											
<b>Comment region</b>	Enables you to comment out highlighted script lines.										
<b>Indent</b>	Indent the selected line or lines of your script.										
<b>Show Snapshot</b>	Show the snapshot associated with the highlighted script step.										
<b>Correlate Selection</b>	Opens Design Studio and scans for dynamic values to be correlated in the selected script section.										
<b>Insert</b>	<table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="text-align: center; padding: 5px;"></td><td style="padding: 5px;">Insert a <b>Start Transaction</b> step into your script. For details, see "<a href="#">Transaction Overview</a>" on page 397.</td></tr> <tr> <td style="text-align: center; padding: 5px;"></td><td style="padding: 5px;">Insert an <b>End Transaction</b> step into your script. For details, see "<a href="#">Transaction Overview</a>" on page 397.</td></tr> <tr> <td style="text-align: center; padding: 5px;"></td><td style="padding: 5px;">Insert a <b>Rendezvous point</b> step into your script. For details, see "<a href="#">Rendezvous Points</a>" on page 400.</td></tr> <tr> <td style="text-align: center; padding: 5px;"></td><td style="padding: 5px;">Insert comments into your script.</td></tr> <tr> <td style="text-align: center; padding: 5px;"></td><td style="padding: 5px;">Insert a <code>lr_log_message("enter message here");</code> into your script.</td></tr> </table>		Insert a <b>Start Transaction</b> step into your script. For details, see " <a href="#">Transaction Overview</a> " on page 397.		Insert an <b>End Transaction</b> step into your script. For details, see " <a href="#">Transaction Overview</a> " on page 397.		Insert a <b>Rendezvous point</b> step into your script. For details, see " <a href="#">Rendezvous Points</a> " on page 400.		Insert comments into your script.		Insert a <code>lr_log_message("enter message here");</code> into your script.
	Insert a <b>Start Transaction</b> step into your script. For details, see " <a href="#">Transaction Overview</a> " on page 397.										
	Insert an <b>End Transaction</b> step into your script. For details, see " <a href="#">Transaction Overview</a> " on page 397.										
	Insert a <b>Rendezvous point</b> step into your script. For details, see " <a href="#">Rendezvous Points</a> " on page 400.										
	Insert comments into your script.										
	Insert a <code>lr_log_message("enter message here");</code> into your script.										
<b>Breakpoints</b>	Toggle Breakpoint.										
<b>Search Community</b>	Opens the default Community Search browser.										

## Thumbnail Explorer

This pane enables you to flip through thumbnail images of your business process, enhancing your ability to navigate to specific locations in the **Editor** based on a visual representation of a step. Conversely, you can scroll through the **Editor** and see the visual context of your script in the **Thumbnail Explorer**.

<b>To access</b>	<p>Use one of the following:</p> <ul style="list-style-type: none"> <li>• <b>VuGen &gt; View &gt;Thumbnail Explorer</b></li> <li>• Click the  button on the VuGen toolbar.</li> </ul>
<b>Important information</b>	<ul style="list-style-type: none"> <li>• You can move this pane to different areas of the Main User Interface. For details see, "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li> <li>• You can configure the <b>Thumbnail Explorer</b> in <b>Options &gt; Scripting Options</b>. For details, see "<a href="#">Scripting Options</a>" on page 103.</li> <li>• Thumbnails are created in the same order as the actions in the Solution Explorer and not controlled by the settings in <b>Run-Time Settings &gt; General &gt; Run Logic</b>.</li> <li>• Enabling automatic creation of thumbnails in <b>Options &gt; Scripting &gt; Thumbnails</b> enables VuGen to create thumbnails during the application's idle time.</li> <li>• If the Windows Aero theme is enabled, thumbnails capture more realistic images of the application.</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Modify the VuGen Layout" on page 93</a>


User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Moves the cursor to the step in the <b>Editor</b> associated with the highlighted thumbnail in the <b>Thumbnail Explorer</b> .
	Enables a full screen view of the thumbnail.
	Synchronizes the scrolling in the <b>Editor</b> with the associated thumbnail in the <b>Thumbnail Explorer</b> and step in the <b>Step Navigator</b> .
	Filters out minor thumbnails that are not directly related to the recorded business process.
	Refreshes the generated thumbnails.
	Scroll a page left in the <b>Thumbnail Explorer</b> .
	Move to the previous thumbnail in the <b>Thumbnail Explorer</b> .
	Move to the next thumbnail in the <b>Thumbnail Explorer</b> .

UI Element	Description
	Scroll a page right in the <b>Thumbnail Explorer</b> .

## Business Process Report Dialog Box

This dialog box enables you to create a business process report.



To access	VuGen > Tools > Create Business Process Report
Relevant tasks	<a href="#">"How to Create a Business Process Report" on page 92</a>

User interface elements are described below:


UI Element	Description
<b>Title</b>	The title of the report.
<b>Author</b>	Your name.

UI Element	Description
<b>Comment</b>	Any additional comments you want to appear in the report.
<b>Location</b>	The path where you want the report to be saved.  <b>Default value:</b> script folder.
 More	Expands the Business Process Report dialog box to display more options.
<b>Table of contents</b>	A table of contents generates for your report. If you disable an option, it will not appear in the table of contents.  <b>Default value:</b> enabled.
<b>Recording summary</b>	A summary of the recording session as it appears when you click the Recording Summary link in the Tasks list.  <b>Default value:</b> enabled.
<b>Transactions and Rendezvous lists</b>	A list of all of the transactions and rendezvous points that were defined in the script.  <b>Default value:</b> enabled.
<b>Parameters list</b>	A list of all the parameters that were defined in the script. This list corresponds to the parameters listed in the Parameter List dialog box <b>Design &gt; Parameter List</b> .  <b>Default value:</b> enabled.
<b>Thumbnails</b>	An actual snapshot of the recorded step, adjacent to the step name and description.  <b>Default value:</b> enabled.
<b>Step descriptions</b>	A short description of each step.  <b>Default value:</b> enabled.
<b>Script name</b>	The .usr file name of the script.
<b>Output format</b>	Creates the report in the selected format. The following formats are available: <ul style="list-style-type: none"> <li>• Microsoft Word</li> <li>• Adobe PDF</li> <li>• HTML</li> </ul>

UI Element	Description
<b>Document template</b>	The path and file name of the template to use for the report. The default template is stored in the LoadRunner's <b>dat</b> folder. To change the report template, click the browse button and specify new template with a .docx extension. If you want to create a new template, we recommend that you use an existing template as a basis for the new one. This will make sure that the required bookmarks and styles are maintained within the new template.

## Steps Toolbox Pane

This pane enables you to drag and drop API functions into your script.

UI example	
	 <p>The screenshot shows the 'Steps Toolbox' window with a toolbar at the top containing a search bar and navigation buttons. Below the toolbar is a list of API functions categorized under 'Common'. Each function is represented by a small icon followed by its name:</p> <ul style="list-style-type: none"><li>Ir_debug_message</li><li>Ir_end_sub_transaction</li><li>Ir_end_transaction</li><li>Ir_end_transaction_instance</li><li>Ir_error_message</li><li>Ir_fail_trans_with_error</li><li>Ir_log_message</li><li>Ir_output_message</li><li>Ir_rendezvous</li><li>Ir_rendezvous_ex</li><li>Ir_resume_transaction</li><li>Ir_save_datetime</li><li>Ir_save_int</li><li>Ir_set_transaction_status_by_name</li></ul>


<b>Important information</b>	<ul style="list-style-type: none"><li>A step's associated parameter dialog box opens when you add the step to the script.</li><li>You can drag and drop steps into your script.</li><li>You cannot drag and drop a step into a step from the <b>Steps Toolbox</b> but you can manually add a step parameter within a step.</li><li>If you insert a step into the incorrect location in your script, the script may fail.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Insert Steps into a Script" on page 406.</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Function List>	Displays a list of available functions divided into the following categories: <ul style="list-style-type: none"><li>Common</li><li>Web checks</li><li>Services</li><li>XML</li><li>Web JS</li><li>Async</li></ul>
 web	<b>Search.</b> Enables you to perform an incremental search in the function list by entering text. For example, if you type "web" into the search box, the function list will display only those function that include the letters "web".
	<b>Add.</b> Add the highlighted step to the current location in your script.
	<b>Expand/Collapse.</b> Expand or collapse the step categories.

## Solution Explorer Pane

This pane enables you to navigate through a solution which contains script assets, parameters, runtime settings, and replay runs.



<b>To access</b>	Do one of the following: <ul style="list-style-type: none"><li>• <b>View &gt; Solution Explorer</b></li><li>• Press <b>Ctrl + Alt + L</b></li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>• Solution Explorer is automatically displayed as part of the default layout.</li><li>• You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li><li>• Other main interface panes such as Output, Error and Snapshot synchronize their displays based on your location in the Solution Explorer.</li><li>• You can double-click an asset to activate it in the editor area or right-click to examine quick operations available for that asset.</li></ul>

<b>See also</b>	<ul style="list-style-type: none"><li>• "<a href="#">VuGen User Interface - Overview</a>" on page 75</li><li>• "<a href="#">Solution Explorer - Overview</a>" on page 80</li><li>• "<a href="#">VuGen Layouts - Overview</a>" on page 79</li><li>• "<a href="#">How to Import Actions to a Script</a>" on page 265</li></ul>
-----------------	--

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Solution>	<p>Container for scripts.</p> <ul style="list-style-type: none"><li>• Default solution name is Untitled.</li></ul> <p><b>Context menu options</b></p> <ul style="list-style-type: none"><li>• Add New Script<ul style="list-style-type: none"><li>For details, see "<a href="#">Create a New Script Dialog Box</a>" on page 170.</li></ul></li><li>• Add Existing Script</li><li>• Save All Scripts</li><li>• Close Solution</li><li>• Save Solution As...</li></ul>

<Script>	<p>Container for script assets including scripts actions, extra files, run-time settings and parameters.</p> <p><b>Context menu options</b></p> <ul style="list-style-type: none"><li>• <b>Save Script</b><p>Select to save script</p></li><li>• <b>Save Script As...</b><p>Save script with new name or to a new location, such as ALM.</p></li><li>• <b>Export to Template....</b><p>You can save scripts as templates. For details, see "<a href="#">How to Create and Open Vuser Script Templates</a>" on page 173.</p></li><li>• <b>Remove Script</b><p>Enables you to delete a script from the solution or select check box to delete from file directory.</p></li><li>• <b>Select file to compare</b><p>You can compare one asset to another. This option selects the highlighted asset as the primary asset.</p></li><li>• <b>Compare to &lt;filename&gt;</b><p>Compares between the selected asset and the primary asset.</p></li><li>• <b>Compare to external file...</b><p>You can compare an asset to a file outside of the solution. This option sets the highlighted asset as the primary asset and opens Windows Explorer to enable you to select the secondary asset.</p></li><li>• <b>Select Folder to Compare</b><p>You can compare one folder to another. This option selects the highlighted folder as the primary folder.</p></li><li>• <b>Compare to External Folder...</b><p>Compares between the selected folder and the primary folder.</p></li><li>• <b>Open Script Folder</b><p>While you record, VuGen creates a series of configuration, data, and source code files. These files contain Vuser run-time and setup information. VuGen</p></li></ul>
----------	--

	<p>saves these files together with the script.</p> <p>You can open the folder on the local disk where the script is saved. For scripts that are saved on a different storage location (such as ALM), this option opens the temporary folder on the local disk.</p>
<b>&lt;Actions&gt;</b>	<p>Container for individual actions including the default actions:</p> <ul style="list-style-type: none"><li>• vuser_init</li><li>• action</li><li>• vuser_end</li></ul> <p><b>Context menu options</b></p> <ul style="list-style-type: none"><li>• Create New Action<ul style="list-style-type: none"><li>Enables you to add a new script action block to your script.</li></ul></li><li>• Import Action<ul style="list-style-type: none"><li>Enables you to import an action from an existing script.</li></ul></li></ul>

<b>Extra Files</b>	<p>Container for extra files associated with your script. You can access these extra files directly from VuGen.</p> <p><b>Context menu options</b></p> <ul style="list-style-type: none"><li>• Create New File<ul style="list-style-type: none"><li>Enables you to create a new file, and then adds the new file to the Extra Files node of your script.</li></ul></li><li>• Add Files to Script<ul style="list-style-type: none"><li>Enables you to add files to the Extra Files node of your script. The files that you add must already exist.</li></ul></li><li>• Add Files Downloaded from HPLN<ul style="list-style-type: none"><li>Enables you to add files to the Extra Files node of your script. The files that you add must have been previously downloaded from HPLN.</li></ul></li><li>• Add Files from Folders and Sub-folders<ul style="list-style-type: none"><li>Enables you to add the contents of folders and sub-folders to the Extra Files node of your script.</li></ul></li></ul> <p>For details on extra files, see "<a href="#">Solution Explorer - Overview</a>" on page 80.</p>
<b>Run-Time Setting</b>	<p>Opens the run-time settings dialog box.</p> <p>For details, see Run-Time Settings Overview.</p>
<b>Parameters</b>	<p>Enables you to create, edit, and list parameters associated with your script. For details, see "<a href="#">Parameters</a>" on page 408.</p> <p><b>Context menu options</b></p> <ul style="list-style-type: none"><li>• Parameters list</li><li>• Create new parameter</li><li>• Edit parameter</li><li>• Configure parameter delimiter</li></ul>

<b>Replay Runs</b>	Enables you to display the Replay Summary report.  <b>Context menu options</b> <ul style="list-style-type: none"><li>• Open Replay Summary<ul style="list-style-type: none"><li>Enables you to open the Replay Summary in the Editor for selected iteration.</li></ul></li><li>• Open Test Results<ul style="list-style-type: none"><li>Enables you to open the Test Results in the Editor for selected iteration.</li></ul></li></ul>
--------------------	--


## Output Pane

The Output pane displays messages that were generated during the recording, compilation, and replay of your script.

<b>To access</b>	Select <b>View &gt; Output</b> , or click the <b>Show Output Pane</b> button  on the VuGen toolbar.
<b>Important information</b>	<ul style="list-style-type: none"><li>• You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">"VuGen Layouts - Overview" on page 79</a>.</li><li>• When you open an existing script, the items displayed in the <b>Output Pane</b> are from the latest replay or compilation.</li></ul>
<b>Relevant tasks</b>	How to Customize the VuGen Layout
<b>See also</b>	<a href="#">"VuGen User Interface - Overview" on page 75</a>

User interface elements are described below:

UI Element	Description
	<p>The type of output to display. The following types are available:</p> <ul style="list-style-type: none"> <li>• <b>Replay.</b> Displays the messages generated by the script replay.</li> </ul> <p><b>Note:</b> If you double-click an entry in the Replay log, VuGen moves the cursor to the corresponding line in the Editor.</p>
	<ul style="list-style-type: none"> <li>• <b>Compilation.</b> Displays the compilation messages.</li> <li>• <b>Code Generation.</b> Displays the code generated during the recording.</li> <li>• <b>Recording.</b> Displays the messages generated during the recording.</li> <li>• <b>Recorded Events.</b> Displays events that occurred during recording.</li> </ul>
	Clears all of the messages from the message list.
	<b>Toggle Line Wrap.</b> When selected, wraps the text of each message onto the next line - as required.
	Jumps to the location in the source document relevant to the selected output message.
	<b>&lt;Find box&gt;.</b> The text string that you want to find. You can refine your search by selecting one of the <b>Options</b> described below. Press <b>ENTER</b> to begin the search.
	<b>Find Previous / Find Next.</b> Highlights the next or previous string that matches the text you entered in the <b>Find</b> box. These buttons are available only after you enter text in the <b>Find</b> box.

UI Element	Description
 Options ▾	<p>Enables you to refine your search with the following options:</p> <ul style="list-style-type: none"> <li>• <b>Match Case.</b> Distinguishes between upper-case and lower-case characters in the search.</li> <li>• <b>Match Whole Word.</b> Searches for occurrences that are only whole words and not part of longer words.</li> <li>• <b>Use Regular Expression.</b> Treats the specified text string as a regular expression.</li> </ul> <p><b>Note:</b> Extended regular expressions and multi-line searches are not supported.</p>
	<p>Opens the Save As dialog box, enabling you to save the contents of the message list as a text file.</p>
<b>View Summary</b> [Available in the Replay log only]	<p>Opens the Replay Summary tab. For details, see "<a href="#">Replay Summary Tab</a>" on page 140.</p>

## Snapshot Pane

<b>To access</b>	Select <b>View &gt; Snapshot</b> , or click the <b>Show Snapshot Pane</b> button  on the VuGen toolbar.
<b>Important information</b>	<ul style="list-style-type: none"> <li>The appearance and functionality of the Snapshot pane vary depending on the protocol of the current Vuser script. In addition to the standard controls, the Snapshot pane may display controls that are specific to the current Vuser protocol.</li> <li>The new Web snapshot model is backward compatible with previous versions of LoadRunner, however some snapshot data may be missing. If this occurs, regenerate the script.</li> <li>When using Windows 2008 R2 and opening a snapshot from the step navigator in SAP GUI and Web protocols, the snapshots might not open automatically. <b>Workaround:</b> Internet Explorer Enhanced Security Configuration must be disabled to view help content. It is enabled by default. (<b>Control Panel &gt; Administrative tools &gt; Server manager &gt; Configure IE ESC</b>).</li> <li>You can move this pane to different areas of the Main User Interface. For details see, "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li> </ul>
<b>See also</b>	<a href="#">"Snapshot Pane - Overview" on page 85</a> <a href="#">"How to Work with Snapshots" on page 88</a>

## Standard Snapshot pane controls

The Snapshot pane displays the following standard controls:

UI Element	Description
	Shows a single snapshot in the Snapshot pane.
	Splits the Snapshot pane to show two snapshots.
	Displays two snapshots in the Snapshot pane - one to the side of the other.
	Displays two snapshots in the Snapshot pane - one above the other.
	Shows the record snapshot in the Snapshot pane.
	Shows the replay snapshot in the Snapshot pane.
Iteration: <input type="button" value="1"/>	Select the iteration number of the replay snapshot to display.
	Synchronizes the display of the two snapshots if the Snapshot pane is split.  Note that snapshot synchronization is available for only specific Vuser protocols, and for only specific views within the protocols.
	Compares the two snapshots that are currently displayed in the Snapshot pane. To enable the <b>Compare</b> functionality, you must first split the Snapshot pane to show two snapshots. By default, VuGen uses the <i>WDiff</i> utility to compare snapshots. You can specify an alternative comparison tool as described in <a href="#">"Scripting Options" on page 103</a> .  Note that the snapshot comparison functionality is available for only the Web HTTP/HTML and Web Services protocols.

## Citrix, RDP, and SAP protocols

User interface elements are described below:

UI Element	Description
	Displays the next record snapshot that was appended during script replay.
	Displays the previous record snapshot that was appended during script replay.
Image	Displays a graphical representation of the snapshot. You can synchronize the display of two snapshots in the Snapshot pane. Snapshots display faster when the Image view is used than when the Full view is used.

Full	Displays a graphical representation of the snapshot. You cannot synchronize the display of two snapshots in the Snapshot pane. Snapshots display slower when the Full view is used than when the Image view is used.
------	--

## Windows Sockets protocol

User interface elements are described below:

UI Element	Description
Hex	Displays the buffer data in hexadecimal.
Text	Displays the buffer data as text.
Go To	Open the Go To Offset dialog box that enables you to navigate within the data buffer.

## Ajax (Click & Script) and Web (Click & Script) protocols

User interface elements are described below:

UI Element	Description
Page View	Displays a graphic view of the Web page.
Page Source	Displays the HTTP source code of the Web page.

## Web (HTTP/HTML) protocol

User interface elements are described below:

UI Element	Description
Page View	Displays step data in HTML format.
Http Data	Displays step data in HTTP format. This enables you to view in-depth information about the step, including request data, response data, cookies, and headers. For more information, see " <a href="#">Web Snapshots - Overview</a> " on page 823.
Grid	(HTTP Data view only) Displays the HTTP flow data in a list format.
Tree	(HTTP Data view only) Displays the HTTP flow data in a tree structure.

## Protocols with an XML request/response (such as Web Services)

User interface elements are described below:

UI Element	Description
------------	-------------


 Response	Displays an XML view of the server response.
 Request	Displays an XML view of the request.
	Opens the XPath search dialog box, allowing you to search the XML code using a standard XPath expression.

<b>&lt;shortcut menu&gt;</b>	<ul style="list-style-type: none"><li>• <b>Copy Selection.</b> Copies the text that is selected in the text view to the clipboard.</li><li>• <b>Search Community.</b> Performs a community search using the text that is selected in the text view as the search string. For details about performing a community search, see "<a href="#">Editor - Overview</a>" on page 82.</li><li>• <b>Copy XPath.</b> In the tree view, copies the XPath of the selected node to the clipboard. In the text view, copies the XPath of the XML element in which the cursor is located to the clipboard.</li><li>• <b>Copy full value.</b> In the tree view, copies the full XML code of the selected node to the clipboard. In the text view, copies the full XML code of the XML element in which the cursor is located.</li><li>• <b>Insert XML Check.</b> Opens the Insert XML Check dialog box that enables you to insert an <b>XML Find</b> step into the Vuser script.</li></ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"><p>This option is available in the Response view only. This option is available for <b>attribute</b>  and <b>value#</b>  nodes only.</p></div> <ul style="list-style-type: none"><li>• <b>Save value in parameter.</b> Opens the Save Value as Parameter dialog box that enables you to save the selected value to a simple parameter.</li></ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"><p>This option is available in the Response view only. This option is available for attribute  and value #  nodes only.</p></div> <ul style="list-style-type: none"><li>• <b>Save XML in parameter.</b> Opens the Save Value as Parameter dialog box that enables you to save the selected value to an XML parameter.</li></ul> <p style="margin-left: 20px;">This option is available in the Response view only.</p> <ul style="list-style-type: none"><li>• <b>Create Correlation.</b> Opens the Correlation tab in the Design Studio. The text selected in the Snapshot pane appears as a manual correlation entry in the Design Studio. For details, see "<a href="#">How To Manually Correlate Scripts</a>" on page 282.</li></ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"><p>This option is available in the Response view only. This option is available for attribute  and value #  nodes in the tree view, and when text is selected in the text view.</p></div> <ul style="list-style-type: none"><li>• <b>Create Correlation Rule.</b> Opens the Add as Rule dialog box that enables you to add the selected text as part of a correlation rule. For details, see "<a href="#">Correlation Tab [Design Studio] Overview</a>" on page 275.</li></ul>
------------------------------	--

	<p>This option is available in the Response view only. This option is available for attribute <code>=#</code> and value <code>#</code> nodes in the tree view, and when text is selected in the text view.</p>
--	--

## Database Protocols

User interface elements are described below:

UI Element	Description
 Recording	Shows the record snapshot in the Snapshot pane.
Data Grid	Displays data in a data grid.

## Bookmarks Pane

The Bookmarks pane displays a list of the bookmarks in your Vuser script. You can navigate between the bookmarks to help analyze and debug your code.

To access	VuGen > View > Bookmarks
Important information	<ul style="list-style-type: none"><li>All bookmarks added to a Vuser script are maintained after you close and reopen the Bookmarks pane.</li><li>You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">"VuGen Layouts - Overview" on page 79</a>.</li></ul>
Relevant tasks	<a href="#">"How to Use Bookmarks" on page 385</a> How to Customize the VuGen Layout
See also	<a href="#">"VuGen User Interface - Overview" on page 75</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):


UI Element	Description
<Bookmarks list>	Displays a list of all bookmarks that are defined in the Vuser script. You can double-click any bookmark line to navigate directly to the relevant line in the Vuser script.
	Toggles the status of the selected bookmark.
	Navigates to previous bookmark in the pane.
	Navigates to next bookmark in the pane.

, continued

	Deletes the selected bookmark.
	Deletes all bookmarks.

## Step Navigator Pane

The Step Navigator pane enables you to navigate to a selected step in your script. If your script contains many steps, you can use the search box to search for matching text in the different parts of the steps.



To access	VuGen > View > Steps
<b>Important information</b>	<ul style="list-style-type: none"><li>You can search within an action or script but not across multiple scripts in a solution.</li><li>You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">"VuGen Layouts - Overview"</a> on page 79.</li><li>You may experience a degradation in performance during replay when the Step Navigator pane is visible. <b>Workaround:</b> Close the Step Navigator pane when replaying a script. You can also set your Replay layout to exclude the Step Navigator pane.</li></ul>

User interface elements are described below:

UI Element	Description

, continued

<b>Search box</b>	You can search different parts of the steps for matching text. The following parts of the steps can be searched: <ul style="list-style-type: none"> <li><b>All.</b> (Default) All parts of the step (name, step, arguments).</li> <li><b>Name.</b> The name of the step.</li> <li><b>Step.</b> The description of the step (for example, web_url, web_custom_request)</li> <li><b>Arguments.</b> The arguments for the step.</li> </ul> Enter the text you want to search for in your steps, in the search edit box and select the part of the steps you want to search. The Steps pane displays only those steps that match your search criteria.
<b>Line</b>	The number of the step in the script.
<b>Name</b>	A step name.
<b>Step</b>	The step type.
 / 	<b>File parser indicator.</b> A green symbol indicates that parsing succeeded and a red symbol indicates that parsing failed.
<b>Action</b>	The action into which the step was created.
<b># steps displayed</b>	Displays the total number of steps in the script or in the action.

## Errors Pane


The Errors pane lists the replay and syntax errors found in your script, and enables you to locate each error so that you can resolve it.

To access	VuGen > View > Errors
<b>Important information</b>	<ul style="list-style-type: none"> <li>You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li> <li>When you open an existing script, the items displayed in the <b>Error Pane</b> are from the latest replay or compilation.</li> </ul>
<b>Relevant tasks</b>	How to Customize the VuGen Layout
<b>See also</b>	<a href="#">"VuGen User Interface - Overview" on page 75</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description

, continued

<b>&lt;Define Available Categories&gt;</b>	Filters the error list by the source of the error.
 Errors: 0	Shows or hides syntax errors.
 Warnings: 0	Shows or hides warnings detected during the run.
 Messages: 0	Shows or hides informational messages detected during the run.
 Locate	Jumps to the line in the Editor that contains the error.
<b>! &lt;Exclamation Point&gt;</b>	Message type: <ul style="list-style-type: none"><li>• Error</li><li>• Warning</li><li>• Informational message</li></ul>
<b>Line</b>	The line containing the error.
<b>Description</b>	Description of the error, warning or message and advice on how to fix the problem. For example, a syntax error is displayed if you opened a conditional block with an If statement but did not close it with an End If statement, the description is Expected Expression. Note: If the description does not fit within the Description column, a tooltip displays the full description when you hover the cursor over the column. In certain cases, VuGen is unable to identify the exact error and displays a number of possible error conditions, for example: Expected 'End Sub', or 'End Function', or 'End Property'. Check the statement at the specified line to clarify which error is relevant in your case.
<b>File</b>	The name of the file that contains the problematic statement.
<b>Path</b>	The full path of the file that generated the error.
<b>Testing Project</b>	The name of the relevant script.

## Task Pane

This pane enables you to add, edit and track tasks associated with an individual script or the overall goals of the project.

<b>To access</b>	<b>VuGen &gt; View &gt; Task Pane</b>
------------------	---------------------------------------

, continued


<b>Important information</b>	You can move this pane to different areas of the Main User Interface. For details see, <a href="#">"VuGen Layouts - Overview" on page 79</a> .
<b>Relevant tasks</b>	How to Customize the VuGen Layout
<b>See also</b>	<a href="#">"VuGen User Interface - Overview" on page 75</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Comments tab</b>	<p>Comment tasks are added directly into your script using the comment syntax of your scripting language and include a keyword such as TODO or FIXME. For example, in C a comment script would look like this:</p> <p>//TODO Add Parameter</p> <p>The Task Pane displays the following information about each task:</p> <ul style="list-style-type: none"><li>• !: Task Type</li><li>• Line: What line the task is located. Double-clicking the task jumps to that location in the script.</li><li>• Description: The Keyword and the task contents.</li><li>• File: Action</li><li>• Path: File location of the action.</li></ul>
<b>User tab</b>	<p>You can add, edit, delete user tasks:</p> <p>Click  to add a task .</p> <p>Click  to edit a task .</p> <p>Click  to delete a task.</p>
<b>&lt;Task Filter&gt;</b>	<p>You can filter tasks associated with a particular script or see all the tasks associated with the solution.</p>

## Breakpoints Pane

The Breakpoints pane enables you to set and manage breakpoints to help analyze the effects of the script on your application at pre-determined points during script execution.



To access	<b>VuGen &gt; View &gt; Debug &gt; Breakpoints</b>
Important information	You can move this pane to different areas of the Main User Interface. For details, see " <a href="#">VuGen Layouts - Overview</a> " on page 79.
Relevant tasks	<a href="#">"How to Debug Scripts with Breakpoints" on page 394</a>

## Breakpoints Pane

User interface elements are described below (unlabeled elements are shown in angle brackets):


UI Element	Description
	Removes the selected breakpoint.
	Removes all breakpoints.
	Locates the cursor in the Vuser script at the line that contains the selected breakpoint.
	Disables the selected breakpoint if it is enabled, and enables the selected breakpoint if it is disabled.
	Allows you to enter conditions for the selected breakpoint. See " <a href="#">Breakpoint Condition Dialog Box</a> on the next page" for more details.
<b>&lt;Breakpoints Grid&gt;</b>	A list of the breakpoints and their locations in the script. To enable a breakpoint, select the <b>Enable</b> check box next to that breakpoint. To disable a breakpoint, clear the <b>Enable</b> check box.
<b>Enabled</b>	A check box that specifies whether the breakpoint is enabled or disabled, and enables you to enable or disable the adjacent breakpoint.
<b>Name</b>	The name of the file that contains the breakpoint, and the line number within the file that contains the breakpoint.
<b>Script</b>	The name of the Vuser script that contains the breakpoint.

, continued

<b>Condition</b>	The condition that applies to this breakpoint. If there is no condition, the replay will always stop at the breakpoint.
<b>Function Name</b>	The name of the function within the Vuser script that contains the breakpoint.

### Breakpoint Condition Dialog Box

The Breakpoint Condition dialog box enables you to condition breakpoints by the iteration number, the value of one or more parameters, or a combination of both parameter values and iteration number.



User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Break when iteration number is</b>	A check box that enables you to specify a breakpoint dependant on the iteration number.
<Operand>	Choose one of the following operands: <ul style="list-style-type: none"><li>• = (equal)</li><li>• &lt;= (less than or equal to)</li><li>• =&gt; (equal to or greater than)</li><li>• &lt; (less than)</li><li>• &gt; (greater than)</li></ul>
<b>to</b>	Enter an iteration number.
<b>Break when Parameter</b>	A check box that enables you to specify a breakpoint dependant on the value of a parameter.

, continued

<Parameter Name>	Choose a parameter from the drop-down list
Value is	Enter the parameter value for which you want a breakpoint.
OK	Apply the conditions to the selected breakpoint. All future replays will only stop at this breakpoint if these conditions are met.

## Watch Pane

The Watch pane enables you to monitor variables while a script runs.

To access	<b>VuGen &gt; View &gt; Debug &gt; Watch</b>
Important information	<ul style="list-style-type: none"><li>This pane is relevant only when a run session is paused.</li><li>You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">"VuGen Layouts - Overview" on page 79</a>".</li></ul>

User interface elements are described below:

UI Element	Description
	Enables you to add a variable to the watch list.
	Enables you to edit the selected variable in the watch list.
	Deletes the selected variable from the watch list.
	Deletes all the variables from the watch list.
<b>Expression</b>	The variable whose value you want to watch.
<b>Value</b>	The current value of the variable. The evaluated value is displayed only when a run session is paused.
<b>Type name</b>	The type of the variable's value after it is evaluated (for example, <b>Integer</b> or <b>Char</b> ). If an variable cannot be evaluated in the current context, the type displayed is <b>Incorrect expression</b> .

## Run Time Data Pane

The Run Time Data pane displays information about the current script execution.

To access	<b>VuGen &gt; View &gt; Debug &gt; Run Time Data</b>
-----------	--

, continued

<b>Important information</b>	<ul style="list-style-type: none"><li>The Run Time Data pane is accessible during script replay only.</li><li>You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li></ul>
<b>Relevant tasks</b>	How to Customize the VuGen Layout
<b>See also</b>	<a href="#">"VuGen User Interface - Overview" on page 75</a> <a href="#">"How to Replay a Vuser Script" on page 316</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Iteration</b>	Displays the current iteration number.
<b>Action</b>	Displays the Action name of the currently replayed step.
<b>Line Number</b>	Displays the line number of the currently replayed step.
<b>Elapsed time</b>	Displays the time that has elapsed since the start of the replay.
<b>&lt;Parameters&gt;</b>	Displays all parameters defined, together with the script and their substitution values based on the selected update method (sequential, unique, etc.). VuGen shows this information even if the parameter is not used in the script.

## Call Stack Pane

This debug pane enables you to view information about the functions that are currently on the call stack of your script.

<b>To access</b>	<b>VuGen &gt; View &gt; Debug&gt; Call Stack</b>
<b>Important information</b>	<ul style="list-style-type: none"><li>This pane is relevant only when a run session is paused.</li><li>You can double-click any element in the Call Stack pane to navigate to the beginning of the relevant function/action.</li><li>This pane is read-only.</li><li>You can move this pane to different areas of the Main User Interface. For details, see "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li></ul>
<b>Relevant tasks</b>	How to Customize the VuGen Layout
<b>See also</b>	<a href="#">"VuGen User Interface - Overview" on page 75</a>

User interface elements are described below:

UI Element	Description
<b>Function name</b>	The name of the function currently called.
<b>File name</b>	The name of the file containing the called function.
<b>Line #</b>	The line number on which the function definition begins.

## Replay Summary Tab

This tab provides summarized replay results and links to script replay details.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• <b>Solution Explorer</b> &gt; Right click <b>Replay Runs</b> &gt; Select <b>Open Replay Summary Tab</b></li><li>• Select <a href="#">View Summary</a> link on the <b>Output Pane</b></li></ul>
<b>Important information</b>	To enable transaction breakdown data, select <b>Options &gt; Scripting &gt; Replay &gt; Collect replay statistics</b>  <b>Caution:</b> Enabling the <b>Collect replay statistics</b> option will affect replay performance.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Output Pane" on page 124</a></li><li>• <a href="#">"How to Replay a Vuser Script" on page 316</a></li></ul>

UI Element	Description
<b>Results Dashboard</b>	<p>Displays basic script information including:</p> <ul style="list-style-type: none"><li>• <b>Script name</b></li><li>• <b>Replay Status</b> Displays a replay status of the script as either <b>Pass</b> or <b>Fail</b>.</li><li>• <b>Elapsed time</b> Total time passed duration script replay.</li><li>• <b>Start time</b> Starting time of the script replay</li><li>• <b>End time</b> Ending time of the script replay</li><li>• <b>Think time</b> Total duration of <b>Think time</b><sup>1</sup> passed during script replay.</li><li>• <b>Wasted time</b> Total duration of <b>Wasted time</b><sup>2</sup> passed during script replay.</li><li>• <b>Select result scope</b> Enables you to select a specific iteration result set from a drop-down or an average of all iterations.</li></ul>

<sup>1</sup>Span of time inserted into a script to simulate a user's pausing before moving on to the next step in a business process.

<sup>2</sup>Time spent on activities whose purpose is to support test analysis, but would never be performed by a browser user.

UI Element	Description
<b>Script Transactions</b>	<p>Displays a list of all transactions in your script with the following statistics:</p> <ul style="list-style-type: none"><li>• Duration: When the scope is a single iteration, the time displayed is the duration of the transaction.  When the scope is an average, the time displayed is the average duration of all iterations.</li><li>• Trend: Sparkline representation of values over all iterations.</li><li>• Status When the scope is a single iteration, the status displayed is either <b>Passed</b> or <b>Failed</b>.  When the scope is an average, the status displayed is the number of transactions with a status of Passed/Total iterations.</li><li>• Size When the scope is a single iteration, the size displayed is the size of the data returned to the client.  When the scope is an average, the size displayed is the average size of the data returned to the client.</li></ul>

UI Element	Description
<b>Connections per domain</b>	<p>Displays statistics by domain per transaction.</p> <p>Note: Statistic available for Web HTTP/HTML protocol scripts only</p> <ul style="list-style-type: none"><li>• <b>Domain name</b> Name of the domain or the IP address of the domain if the name is not found.</li><li>• <b>Count</b> When the scope is a single iteration, the count displayed is the number of connections to the server per domain.  When the scope is an average, the count displayed is an average of connection to the server per domain.</li><li>• <b>Count %</b> When the scope is a single iteration, the count % represents the percentage of connections to the server per domain.  When the scope is an average, the count % represents the average percentage of connections to the server per domain.</li><li>• <b>Hit count</b> When the scope is a single iteration, the hit count displayed is the number of files requested from the server.  When the scope is an average, the hit count displayed is the average number of files requested from the server.</li><li>• <b>Size</b> When the scope is a single iteration, size displayed is the size of the data returned from the server per domain.  When the scope is an average, size displayed is the average size of the data returned from the server per domain .</li><li>• <b>Size %</b> When the scope is a single iteration, size % represents the percentage of data returned from the server per domain from the total returned data.  When the scope is an average, size % represents the average percentage of data returned from the server per domain from the total returned data</li><li>• <b>Trend</b> Sparkline representation of values over all iterations.</li></ul>

UI Element	Description
	<ul style="list-style-type: none"><li>• DNS time</li></ul> <p>When the scope is a single iteration, DNS time displayed is the amount of time it takes the web browser to translate a hostname to its corresponding IP address.</p> <p>When the scope is an average, DNS time displayed is the average amount of time it takes the web browser to translate a hostname to its corresponding IP address.</p>

UI Element	Description
<b>Connections per content type</b>	<p>Displays statistics by content type per transaction.</p> <p>Note: Statistic available for Web HTTP/HTML protocol scripts only</p> <ul style="list-style-type: none"><li>• <b>Content type</b><p>List of the content type returned from the server, for example, an image, a JavaScript, a CSS.</p></li><li>• <b>Count</b><p>When the scope is a single iteration, the count is displayed is the number of connections per content type.</p><p>When the scope is an average, the count is displayed is the average number of connections per content type.</p></li><li>• <b>Count %</b><p>When the scope is a single iteration, the count % represents the percentage of connections to the server content type.</p><p>When the scope is an average, the status displayed is the average percentage of connections to the server content type from the total number of connections.</p></li><li>• <b>Size</b><p>When the scope is a single iteration, size displayed is the size of the data returned from the server for each content type.</p><p>When the scope is an average, size displayed is the average size of the data returned from the server for each content type.</p></li><li>• <b>Size %</b><p>When the scope is a single iteration, size % represents the percentage of data returned from the server for each content type from the total returned data.</p><p>When the scope is an average, size % represents the average percentage of data returned from the server for each content type from the total returned data.</p></li><li>• <b>Trend</b><p>Sparkline representation of values over all iterations.</p></li></ul>

UI Element	Description
<b>Connections per HTTP Status</b>	<p>Displays statistics by HTTP Status per transaction.</p> <p>Note: Statistic available for Web HTTP/HTML protocol scripts only</p> <ul style="list-style-type: none"> <li>• <b>Status</b> List of the HTTP status codes returned by the transaction.</li> <li>• <b>Count</b> When the scope is a single iteration, the count displayed is the number of connections HTTP status code per transaction.  When the scope is an average, the count displayed is the average number of connections per HTTP status code per transaction.</li> <li>• <b>Count %</b> When the scope is a single iteration, the count is displayed is the percentage of connections per HTTP status code per transaction.  When the scope is an average, the count is displayed is the average percentage of connections per HTTP status code per transaction.</li> <li>• <b>Trend</b> Sparkline representation of values over all iterations.</li> </ul>
<b>Replay Statistics Summary</b>	<p>A list of script statistics and their values after replay.</p>
More information is available in:	<ul style="list-style-type: none"> <li>• <b>Test Results</b> For details, see "<a href="#">Test Results Window</a>" on page <a href="#">482</a>.</li> <li>• <b>Replay Log</b></li> </ul>
<b>&lt;Modify Run-Time Settings&gt;</b>	<p>Enables you to access <b>Run-Time Settings</b> for your active script.</p>
<b>&lt;Modify Content Check Rules&gt;</b>	<p>VuGen's <b>ContentCheck</b> mechanism enables you to detect all types of errors sent by the web server.</p> <p>For details, see "<a href="#">Internet Protocol &gt; ContentCheck Node</a>" on page <a href="#">351</a>.</p>

## VuGen - Troubleshooting and Limitations

This section describes troubleshooting and limitations for the VuGen.

### Troubleshooting Snapshots

If you encounter a step without a snapshot, follow these guidelines to determine why it is not

available. Note that not all steps are associated with snapshots—only steps with screen operations or for Web, showing browser window content, have snapshots.

Several protocols allow you to disable the capturing of snapshots during recording using the Recording options.

If there is no **Record** snapshot displayed for the selected step, it may be due to one of the following reasons:

- The script was recorded with a VuGen version 6.02 or earlier.
- Snapshots are not generated for certain types of steps.
- The imported actions do not contain snapshots.

If there is no **Replay** snapshot displayed for the selected step, it may be due to one of the following reasons:

- The script was recorded with VuGen version 6.02 or earlier.
- The imported actions do not contain snapshots.
- The Vuser files are stored in a read-only folder, and VuGen could not save the replay snapshots.
- The step represents navigation to a resource.

## Internet Explorer and Windows Server Machines

When using Internet Explorer on Windows server machines such as Windows Server 2008 and 2012, the browser's enhanced security (ESC) blocks certain actions and issues the following message: "Content from the Web site listed below is being blocked by the Internet Explorer Enhanced Security Configuration." This prevents the automatic download of files that are necessary for your workflow.

**Workaround:** Add an entry "about:internet" to the Trusted Sites in Internet Explorer.

## Memory Issues

If the script is extremely large in size, you may encounter problems opening the script if the memory on the machine is insufficient. To reduce VuGen memory usage, select **Tools > Options** and clear the **Enable C language parser** check box to disable the C Parser. Note that this will affect some of the graphic-related features, such as Step Navigation and Thumbnails.

# Protocol Advisor - Overview

You use the Protocol Advisor to help you determine an appropriate protocol for recording a Vuser script. The Protocol Advisor scans your application for elements of different protocols and displays a list of the detected protocols. These protocols should be used as guidelines and as a starting point for finding the optimal protocol for your application.

In most cases, the Protocol Advisor suggests more than one protocol, along with combinations of protocols. For guidelines on how to use the list of suggested protocols, see "[How to use the Protocol Advisor](#)" on the next page.

# How to use the Protocol Advisor

This task describes a typical workflow for finding the optimal protocol to record your application using the Protocol Advisor.

## 1. Start the Protocol Advisor

In VuGen, select **Record > Protocol Advisor > Analyze Application**.

If you are analyzing a web application, you will need to specify:

- Program to analyze
- URL Address
- Working Directory

If you are analyzing a Windows application, you will need to specify:

- Program to analyze
- Program arguments, if any
- Working Directory

For details, see "[Protocol Advisor Dialog Box](#)" on page 150.

## 2. Perform typical business processes

Perform typical business processes in your application. Try to walk through a variety of business processes to make sure that your results are comprehensive. Click **Stop Analyzing** to end the analysis and display the results.

## 3. Save the results

Select **Record > Protocol Advisor > Save Results** or click **Save Results** from the toolbar at the top of the report. Enter a name and select the folder.

To display a previous report, select **Record > Protocol Advisor > Recent reports**. VuGen will maintain a history of the last sixteen Protocol Advisor reports generated. To clear the history, select **Record > Protocol Advisor > Clear Recent Reports**.

## 4. Select a protocol and create a new Vuser script

Select one of the protocols using the following order of priority and create a Vuser script using that protocol:

- Multi/Combination protocol
- The highest level application protocol


- The first protocol on the list

## 5. Enhance, debug, and verify replay

Enhance and debug your script until you can replay it successfully. If, after enhancing and debugging the Vuser script, you cannot replay it successfully, proceed to the next step.

## 6. If the replay is unsuccessful, select a different protocol and repeat

- **For all non Web-based protocols:** Return to the Protocol Advisor Results page and select the next protocol on the list and repeat previous steps. If there are no more protocols listed, contact HP Customer Support.
- **For Web-based protocols:** The following diagram illustrates several Web-based protocols arranged according to their application level. The arrows indicate the order in which you should attempt a new protocol. For example, if the first protocol you used was Oracle Web Applications 11i and it failed to successfully replay, you would then try the Oracle NCA protocol.



## Protocol Advisor Dialog Box

This dialog box enables you to analyze your application to determine the appropriate VuGen protocols to use for recording.

<b>To access</b>	Do one of the following: <ul style="list-style-type: none"><li>• <b>VuGen &gt; Record &gt; Protocol Advisor &gt; Analyze Application</b></li><li>• <b>VuGen &gt; File &gt; New Script and Solution &gt; Protocol Advisor</b></li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>• The options in this dialog box change according to the selection you make for <b>Application type</b>.</li></ul>

, continued

<b>Relevant tasks</b>	<a href="#">"How to use the Protocol Advisor" on page 148</a>
-----------------------	---

User interface elements are described below:

UI Element	Description
<b>Application type</b>	Windows or Web application.
<b>Program arguments (Win32 Applications only)</b>	Specify command line arguments for the executable specified above. For example, if you specify <i>plus32.exe</i> with the command line options <i>peter@neptune</i> , it connects the user <i>Peter</i> to the server <i>Neptune</i> when starting <i>plus32.exe</i> . This option is displayed only for Windows applications.
<b>Program to analyze</b>	Select the browser, Web application, or Windows application to analyze.
<b>URL Address (Internet Applications only)</b>	The starting URL address. This option is displayed only for Web applications.
<b>Working directory</b>	The working directory for your application, if needed.

## Protocol Advisor - Troubleshooting and Limitations

This section describes troubleshooting and limitations for the Protocol Advisor.

- This feature will only detect protocols supported by LoadRunner.
- Some Web protocols are detected based on the URL. For example, the URL may contain keywords such as SAP. Therefore, if you use a different URL or a different application with the same URL, the results may differ.
- The following protocols are frequently detected but are not always appropriate for use. You should only use them if there are no other detected protocols.
  - COM/DCOM
  - Java
  - .NET
  - WinSock
  - LDAP

- If you terminated the Protocol Advisor immediately after the detection process started, the Protocol Advisor may leave a hanging process of the detected application, causing all recordings and detection sessions that follow to fail.

**Workaround:** Manually terminate the hanging process.

## HP Live Network (HPLN) Integration

HP Live Network (HPLN) provides you with additional software content and information about your HP Software products. The LoadRunner HPLN Integration feature enables you to download and upload content that can then be shared by other LoadRunner users.

You can download and upload the following content types to and from HPLN:

- Action/Function files with .c, .java, .js, and .cs extensions.

**Note:** For security reasons, .js files must be zipped before uploading to HPLN, and unzipped after downloading from HPLN.

- Correlation files with the .cor extension
- Data Format Extension (DFE) files with the .vucsx extension
- VuGen add-in files with a .zip extension


For more information on how to use HPLN, use the following table:

How to ...	UI Descriptions
<ul style="list-style-type: none"><li>• "<a href="#">How to Download Content from HP Live Network (HPLN) to LoadRunner</a>" below</li><li>• "<a href="#">How to Upload Content from LoadRunner to HP Live Network (HPLN)</a>" on page 154</li></ul>	<ul style="list-style-type: none"><li>• "<a href="#">HP Live Network Connection Dialog Box</a>" on page 157</li><li>• "<a href="#">Download from HP Live Network Dialog Box</a>" on page 158</li></ul>

## How to Download Content from HP Live Network (HPLN) to LoadRunner

The following task describes how to download content from HPLN and import it into your LoadRunner project.

The flow for downloading content to LoadRunner is as follows:



1. On the VuGen main Toolbar, click **HPLN**, and log in to HPLN.

If you are already logged on, you will be automatically directed to the HPLN download page.

**Note:** The first time you log in to HPLN in a VuGen session may take several minutes whilst the dynamic content page is created. The subsequent loading of the content page is much quicker.

For more information on logging in to HPLN, see "["HP Live Network Connection Dialog Box" on page 157](#)".

2. On the **Download from HP Live Network** screen, select the relevant HPLN Content type, and on the relevant content, click **Download** to download the content.

When you click **Download**, the status **Downloading** appears, and when the selected file has been downloaded the status changes to **Downloaded**.

**Note:** Downloaded content is saved in the relevant sub-folder of %programdata%\Hewlett-Packard\LoadRunner\HPLN.

For more information on downloading content, see "["Download from HP Live Network Dialog Box" on page 158](#)".

3. To use the content in LoadRunner, depending on the type of content you downloaded, perform the following steps:

**a. Actions/Functions content**

- i. If you downloaded a .zip file containing a.js file, you must unzip the .js file before you can add the file as an extra file.
- ii. In Solution Explorer, for the script you are developing, right-click **Extra Files** and select **Add Files Downloaded from HPLN**.
- iii. Then in the %programdata%\Hewlett-Packard\LoadRunner\HPLN\function folder, select the relevant function file, and click **Open**.

**b. Correlation content**

- i. On the VuGen main menu, select **Record > Recording Options > Correlations - Rules**, and click **Import**.
- ii. In the %programdata%\Hewlett-Packard\LoadRunner\HPLN\cor folder select the correlation file, and click **Open**.


**c. DFE content**

- i. On the VuGen main menu, select **Record > Recording Options > Data Format Extension - Code Generation**.
- ii. Select **Enable data format extension** and click **Import**.  
  
If you are prompted with a message "This operation will overwrite the current settings", and you wish to overwrite the current settings, click **Yes**.
- iii. In the %programdata%\Hewlett-Packard\LoadRunner\HPLN\dfe folder, select the DFE file, and click **Open**.

## How to Upload Content from LoadRunner to HP Live Network (HPLN)

The following task describes how to upload content from LoadRunner to HPLN.

The flow for uploading content from LoadRunner to HPLN is as follows:



1. Export the content you want to upload to a file as follows:

### Actions/Functions content

Locate the action or function file in preparation for uploading to HPLN.

**Note:** If you are uploading a .js file, for security reasons you must zip the .js file and upload the zip file.

### Correlation content

- a. On the VuGen main menu, select **Record > Recording Options > Correlations - Rules**
- b. Click **Export**, select an **Application to Export**, and then click **Export**
- c. Enter a filename and location, and then click **Save**.

**Note:** The file is saved by default in the %programdata%\Hewlett-Packard\LoadRunner\HPLN\cor folder.

### DFE content

- a. On the VuGen main menu, select **Record > Recording Options > Data Format Extension - Code Generation**
- b. Select **Enable data format extension**, and then click **Export**.
- c. Enter a filename and location, and then click **Save**.

**Note:** The file is saved by default in the %programdata%\Hewlett-Packard\LoadRunner\HPLN\dfe folder.

## 2. Log in to HPLN

On the VuGen main Toolbar, click  HPLN, and log in to HPLN.

**Note:** The first time you log in to HPLN in a VuGen session may take several minutes whilst the dynamic content page is created. The subsequent loading of the content page is much quicker.

**Note:** If you are already logged in, you will be automatically directed to the HPLN download page.

3. On the Download from HP Live Network screen, click **Upload Content to HPLN** .

4. In the main HPLN screen, Click the **Content** tab, and click **Add Content**.

### 5. Start the upload procedure

Enter the following information:

- a. The name and description for the content.

**Note:** The name and description content are used when searching the content in the Download from HP Live Network screen.

- b. The supported product versions.

**Note:** When the system prepares the content list for the Download from HP Live Network screen, it displays content that is relevant to the version of VuGen you are using.

- c. The version

Enter a version number. A version number is automatically generated the first time you add content. The version number for content is unique per update. If you in the future update the specific content, you must enter a different version number.

- d. The content type

Select the relevant content type.

**Note:** The content is delivered and selected according to the content type. lr\_cr for correlation content, lr\_dfe for DFE content and lr\_ff for Action/Function content.

## 6. Attach the content


Click **Add Content Attachment**.

On the Create Content Attachment screen:

- a. Enter the name and version, and then click the **File attachments** tab.
  - b. Click **Choose file**, select the content file you want to upload, and then click **Finish**.
7. After reviewing the summary, click **Publish**, and on the **You are about to Publish** screen, click **Submit**.

## HP Live Network Connection Dialog Box

This dialog box enables you to log in to HP Live Network (HPLN), and gives you access to the HPLN content files.



The image shows the 'HP Live Network Connection' dialog box. It has fields for 'User ID' and 'Password'. Below these is a 'Proxy Setting' section with fields for 'Proxy URL', 'Proxy username', and 'Proxy password'. There is a checked checkbox for 'Remember my credentials'. At the bottom, there is a link 'Get an HP Passport: <https://passport2.hp.com/hpp/login.do>' and a 'Login' button.

HP Live Network Connection	
User ID:	<input type="text"/>
Password:	<input type="password"/>
Proxy Setting	
Please enter proxy information below (optional)	
Proxy URL:	<input type="text"/>
Proxy username:	<input type="text"/>
Proxy password:	<input type="password"/>
<input checked="" type="checkbox"/> Remember my credentials	
Get an HP Passport: <a href="https://passport2.hp.com/hpp/login.do">https://passport2.hp.com/hpp/login.do</a>	
<input type="button" value="Login"/>	


To access	Use one of the following: <ul style="list-style-type: none"><li>From the main VuGen toolbar, click <b>HPLN</b>.</li><li>On the main VuGen menu, select <b>Tools &gt; Reset Credentials</b></li></ul>
Important information	If you select <b>Remember my credentials</b> , this HP Live Network Connection dialog box appears only when you choose to Reset Credentials. <p><b>Note:</b> When you access HPLN for the first time in a session, the feature may take several minutes to populate the Download from HPLN window.</p>
Relevant tasks	<a href="#">"How to Download Content from HP Live Network (HPLN) to LoadRunner" on page 152</a> <a href="#">"How to Upload Content from LoadRunner to HP Live Network (HPLN)" on page 154</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
User Id	Enter your Passport ID.
Password	Enter your Passport ID password.
Proxy Setting	If you access the Internet via a proxy and your proxy settings are not automatically configured on your machine, enter the following proxy details: <b>Proxy URL.</b> The URL of your proxy server. <b>Proxy username.</b> Your proxy user name. <b>Proxy password.</b> Your proxy password.
<Remember my credentials>	When selected, your previous credentials are used to log in to HPLN. <p><b>Note:</b> To log in as a different user, on the main VuGen menu, select <b>Tools &gt; Reset Credentials</b>.</p>
Login	Click to log in to HPLN.

## Download from HP Live Network Dialog Box

This dialog box enables you to download content files from HPLN.



<b>To access</b>	Use one of the following: <ul style="list-style-type: none"> <li>From the main VuGen toolbar, click <b>HPLN</b>.</li> <li>On the main VuGen menu, select <b>Tools &gt; HPLN</b></li> </ul>
<b>Important information</b>	<ul style="list-style-type: none"> <li>If you are not logged on to HPLN, you will be directed to the HP Live Network Connection dialog box.</li> <li>If you are already logged on to HPLN, the Download from HPLN Dialog box appears.</li> </ul> <p><b>Note:</b> When you access HPLN for the first time in a session, the feature may take several minutes to populate the Download from HPLN window.</p> <ul style="list-style-type: none"> <li>The Close button, closes the dialog box, and completes the downloading of content currently selected for download.</li> <li>You can only use one HPLN session at any time on a server. If you have more than one VuGen open, you cannot access HPLN from both sessions simultaneously.</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Download Content from HP Live Network (HPLN) to LoadRunner" on page 152</a> <a href="#">"How to Upload Content from LoadRunner to HP Live Network (HPLN)" on page 154</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Refresh Content.</b> Repopulates the HPLN list of content available for download.
	<b>Open Content Folder.</b> Opens the folder where the content was downloaded to.  <div style="background-color: #f0f0f0; padding: 5px;"><b>Note:</b> Because the filename is not displayed on screen, you can use this option to see the name of the downloaded content file.</div>
	<b>Upload Content to HPLN.</b> Directs you to the HPLN upload site. You can share content with other LoadRunner users by uploading content to this location.  <div style="background-color: #f0f0f0; padding: 5px;"><b>Note:</b> You require content contributor permissions to upload content to HPLN. These can be provided by the community owner.</div>
	Pauses all pending downloads.
	Cancels all pending downloads.
<HPLN Content>	Lists the content types that you can download. The content types are: Actions/Functions, Correlation Rules, and DFE files.
<Search>	Enter a string of text, and the displayed list of content automatically updates to reflect the search text entered. All the text entered when the asset is created on HPLN is included in the text search.
<Asset Action/Status>	The following actions/statuses can be displayed for a content item: <ul style="list-style-type: none"> <li>• <b>Download.</b> Click to download a content file. Once the content has been successfully downloaded, the <b>Re-Download</b> button appears.           The number of content files being downloaded is displayed on the bottom of the <b>Download from HP Live Network</b> window.           If you to download several content files simultaneously, the first is downloaded and the other content files are put in a state of <b>Pending</b>. When the first download is complete, the downloading of the next content file begins.       </li> <li>• <b>Re-Download.</b> Click to re-download a content file.</li> <li>• <b>Paused.</b> Displayed when the download of a content file is paused by clicking the <b>Pause</b> button. Click <b>Download</b> to re-initiate the download of the content file.</li> </ul>

UI Element	Description
<b>&lt;Progress Bar&gt;</b>	Displays the progress of the download. If you download several content files, the number of downloads will be displayed in the format "Downloading item x of y from HPLN".
 Close	Closes the dialog, but completes in the background the downloading of selected content.

# Script Workflow


The **Script Workflow** section provides detailed information about the workflow to be followed to develop a Vuser script.

## How to Create or Open a Vuser Script

This section describes how to create new Vuser scripts, and open existing Vuser scripts.

### Creating Vuser Scripts - Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the first step, creating a Vuser script.



The first step in developing a Vuser script is to create a blank script. For details on how to create a blank Vuser script, see "[How to Create and Open Vuser Scripts](#) on the next page". The contents and structure of the blank Vuser script vary slightly based on the protocol of the script. Therefore, before you create a blank Vuser script, you must know the protocol to use for the script. You can use the Protocol Advisor to help you to select a protocol. The Protocol Advisor scans your application for elements of different protocols and displays a list of the protocols that it detects. For details, see [Protocol Advisor](#). After you create a blank Vuser script, you are ready to perform the next step in the script creation workflow - recording user actions into the script. For details, see "[Recording a Vuser Script](#)" on page 174.

When you create a Vuser script, VuGen creates a series of configuration files, data files, and source code files that comprise the Vuser script. These files contain Vuser run-time and setup information. For details on the files that comprise a Vuser script, see "[Script Directory Files](#)" on page 170.

VuGen enables you to:

- Create or open a script from a template. For task details, see "[How to Create and Open Vuser Script Templates](#)" on page 173.
- Open or work with a .zip script. You can unzip or work with a script in .zip format. For task details, see "[How to Work with .zip Files](#)" on page 172.
- Open a script stored in Application Lifecycle Management. For more information, see "[Working with Application Lifecycle Management](#)" on the next page.
- Use *HP Application Lifecycle Management* (ALM) to store and retrieve Vuser scripts, scenarios, and analysis results. You can store scripts in an ALM project and organize the scripts into unique groups. For more information, see "[Managing Scripts Using ALM - Overview](#)" on page 164.

# How to Create and Open Vuser Scripts

This task describes various ways to create a new Vuser script or to open an existing Vuser script.

## Create a new Vuser script

1. Open VuGen and select **File > New Script and Solution**.
2. In the **Create a New Script** dialog box, select **Single Protocol** or **Multiple Protocols** from the **Category** list.
3. Select a protocol from the **Protocols** list.
4. In the **Script Name** box, enter a name for the script.

**Note:** Do not name scripts *init*, *run* or *end*, since these names are used internally by VuGen.

5. Click **Create** to create the Vuser script.

For user interface details, see "[Create a New Script Dialog Box](#)" on page 170.

After you create a new Vuser script, you can record user activity into the script. For details, see "[How to Record a Vuser Script](#)" on page 175.

## Create or open a script from a template

For task details, see "[How to Create and Open Vuser Script Templates](#)" on page 173.

## Open an existing script

To open an existing script that is saved on your local machine or on a network drive, select **File > Open > Script/Solution**.

## Open or work with a .zip script

You can unzip or work with a script in .zip format. For task details, see "[How to Work with .zip Files](#)" on page 172.

## Open a script stored in Application Lifecycle Management

You can store scripts on HP ALM and modify them in VuGen. For more information, see "[Working with Application Lifecycle Management](#)" below.

# Working with Application Lifecycle Management

The **Working with Application Lifecycle Management** section describes who to manage your Vuser scripts by integrating with Application Life Cycle Management.

## **Managing Scripts Using ALM - Overview**

VuGen works together with *HP Application Lifecycle Management* (ALM). ALM provides efficient functionality for storing and retrieving Vuser scripts, scenarios, and analysis results. You can store scripts in an ALM project and organize the scripts into unique groups.

In order for VuGen to access an ALM project, you must connect VuGen to the Web server on which the ALM project is located. You can connect to either a local or remote Web server.

For more information on working with ALM, see the *HP Application Lifecycle Management User Guide*.

## **ALM Version Control - Overview**

VuGen supports version control features in Vuser scripts saved in ALM projects that use version control.

The version control features change the process of opening and saving a script. Scripts with version control are either in a state of checked-in or checked-out. When you are working with a script in a checked-out state, any changes you make will not be saved on the ALM server until you check in the script. If you save the script from within VuGen, a temporary file is saved on your machine that protects your changes in case your computer crashes.

If you are working with a script in a checked-in state, the script is read-only and you cannot make any changes until you check out the script.

If a particular script is being saved to ALM for the first time, and the project uses version control, the script automatically starts in a checked-out state.

## **How to Work with Scripts in ALM Projects**

The following steps describe the workflow of how to work with Vuser scripts that are saved in an ALM project.

**Note:** To work with scripts in ALM projects with version control, see "[How to Work with Version Controlled Scripts in ALM Projects](#)" on the next page.

### **1. Connect to ALM**

Open a connection to the ALM server and project that contains the script. For task details, see "[How to Connect to ALM](#)" on the next page.

### **2. Open the script**

Select **File > Open > Script/Solution**. In the Open VuGen Script or Solution dialog box, select the script to open and then click **Open**.

### **3. Save the script**

Select **File > Save Script**. If the script is in a project that uses version control and is not checked out, the script is saved as a temporary file on your local machine.

## How to Connect to ALM

To store and retrieve scripts from ALM, you need to connect to an ALM project. You can connect or disconnect from an ALM project at any time during the testing process.

You can connect to one version of HP ALM from VuGen and a different version from your browser. For more information, see the **Important Information** section in "["HP ALM Connection Dialog Box \[VuGen\]" on page 167](#).

### Connect to a project in ALM

1. Determine the type of authentication required for the ALM server: User name/password or CAC (Common Access Card). For CAC mode, enable CAC authentication in VuGen's **General** options. For details, see "["General Options" on page 95](#).
2. Select **ALM > ALM Connection**. The HP ALM Connection dialog box opens.
3. In the **Step 1: Connect to server** section, enter a user name and password (not relevant for CAC authentication) and click **Connect**. VuGen connects to the ALM server.  
To disconnect from ALM, click **Disconnect**.
4. In the **Step 2: Login to project** section, enter the domain and project details, and then click **Login**. VuGen logs in to the specified project.  
To log out of the project, click **Logout**.
5. Click **Close** to close the HP ALM Connection dialog box.

## How to Work with Version Controlled Scripts in ALM Projects

The following steps describe the workflow of how to work with scripts saved in ALM projects that use version control.

**Note:** This procedure is relevant only for scripts in ALM projects that support version control and have the Performance Center addition installed. If these two conditions are not met, see "["How to Work with Scripts in ALM Projects" on the previous page](#).

### 1. Connect to ALM

Open a connection to the ALM server and project that contains the script. For task details, see "["How to Connect to ALM" above](#).

## 2. Open the script

Select **File > Open > Script/Solution**. In the Open VuGen Script or Solution dialog box, select the script to open and then click **Open**.

## 3. Check in/out the script

If the ALM project has version control, each script is always defined as being either checked-in or checked-out. For more details, see "[ALM Version Control - Overview](#)" on page 164. To check in and check out scripts, select **ALM > Check In/Check Out**.

**Note:** If the ALM project has version control, the file is locked when it is checked out.

If the ALM project is not version controlled, the file is not locked when checked out of the project.

## 4. Cancel a check out (optional)

If you checked out a script and do not want to save the changes, you can return the status of the script to checked-in without saving by selecting **ALM > Undo Check Out**.

## 5. Save the script

Select **File > Save Script**. If the script is in a project that uses version control and is not checked out, the script is saved as a temporary file on your local machine.

# How to Save VuGen Vuser Scripts to ALM Projects

The following steps describe how to save a Vuser script to an ALM project.

## 1. Open or create the Vuser script


Create or open the desired script in VuGen.

## 2. Connect to ALM

Open a connection to the ALM server and project in which you want to store the script. For task details, see "[How to Connect to ALM](#)" on the previous page.

## 3. Save the script to ALM

- a. Select **File > Save Script as**. The Save Script As dialog box opens.
- b. Click **ALM Test Plan**, and then specify the name and location for the script.
- c. Click **Save**. After a short time, the Working Mode dialog box opens.



- d. Select one of the following options:

**Runtime Mode.** Copies only the files needed to replay the script. This option does not copy recording snapshot files and other unnecessary files. This results in a shorter transfer time.

**All Files Mode.** Copies all of the files associated with this script. This results in a longer transfer time.

## How to Compare Previous Versions of a Script

If your Vuser script is saved in an ALM project that uses version control, you can compare previous versions of the script. The following steps describe how to do this.

### 1. Connect to ALM

Open a connection to the ALM server and project that contains the script that you want to view or modify. For task details, see "[How to Connect to ALM](#)" on page 165.

### 2. Open the script


Select **File > Open > Script/Solution**. In the Open VuGen Script or Solution dialog box, select the script to open and then click **Open**.

### 3. Compare previous versions of the script

- Select **ALM > Version History**. The Version History dialog box opens.
- Select two previous versions of the script and then click **Compare Versions**. WDiff opens and displays the two versions of the script.

## HP ALM Connection Dialog Box [VuGen]


This dialog box enables you to connect to an HP ALM project from within VuGen.



To access	ALM > ALM Connection
<b>Important information</b>	<ul style="list-style-type: none"><li>You can connect to one version of HP ALM from VuGen and a different version of HP ALM from your browser.</li><li>You can connect to different versions of HP ALM only if one of the versions is HP ALM 11.00 or higher.</li></ul> <p><b>Note:</b> Before you connect to results stored on ALM through the this dialog box, it is recommended that you first connect to the HP ALM server through your browser. This automatically downloads the ALM client files to your computer.</p> <ul style="list-style-type: none"><li>You can configure more advanced settings, such as a proxy setting, by using the Webgate Customization tool (webgatecustomization.exe) and then sign into ALM using the HP ALM Connection Dialog Box. The Webgate Customization tool can be found on your ALM server at the following address: <a href="http://&lt;ALM Server&gt;/qcbin/Apps/">http://&lt;ALM Server&gt;/qcbin/Apps/</a>.</li></ul>

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Step 1: Connect to Server</b>	<ul style="list-style-type: none"><li>• <b>Server URL.</b> The URL of the server on which ALM is installed.</li><li>• <b>User name.</b> Your ALM project user name (not relevant for CAC authentication).</li><li>• <b>Password.</b> Your ALM project password (not relevant for CAC authentication).</li><li>•  . Connects to the server specified in the <b>Server URL</b> box.</li><li>• <a href="#">Disconnect</a>. Disconnects from the current ALM server.</li></ul>
<b>Step 2: Login to Project</b>	<ul style="list-style-type: none"><li>• <b>Domain.</b> The domain that contains the ALM project. Only those domains containing projects to which you have permission to connect to are displayed.</li><li>• <b>Project.</b> Enter the ALM project name or select a project from the list. The list includes only those projects to which you have permission to connect.</li></ul> <ul style="list-style-type: none"><li>•  . Logs into the ALM project.</li><li>• <a href="#">Logout</a>. Logs out of the current ALM project.</li></ul>
<b>Restore connection on startup</b>	Automatically reconnect to the ALM server the next time you start VuGen, using the same credentials.

## Multiple Protocol Scripts

When you record a single protocol, VuGen records only the specified protocol. When you record in multi-protocol mode, VuGen records the actions in several protocols. Multi-protocol scripts are supported for the following protocols: COM, FTP, IMAP, Oracle NCA, POP3, Window Sockets (raw), SMTP, and Web.

Another variation between Vuser types is multiple-action support. Most protocols support more than one action section. Currently, the following protocols support multi-actions: Oracle NCA, Web, RTE, General (C Vusers), WAP, and VoiceXML.

For most Vuser types, you create a new Vuser script each time you record—you cannot record into an existing script. However, when recording a Java, Web, WAP, Oracle NCA, or RTE Vuser script, you can also record within an existing script.

Since VuGen supports a large variety of protocols, some of the recording steps that follow apply only to specific protocols.

For all Java language Vusers see ["Java Protocols" on page 650](#).

## Script Directory Files

While you create a Vuser script, VuGen creates a series of configuration files, data files, and source code files that comprise the Vuser script. These files contain Vuser run-time and setup information. VuGen saves these files together with the script, in the script folder. To access the files in the script folder, right click on the script name in the **Solution Explorer** and select **Open Script Folder**.

	data	5/6/2013 4:27 PM	File folder
	Action	5/6/2013 4:28 PM	C Source 25 KB
	AsyncCallbacks	5/6/2013 4:27 PM	C Source 9 KB
	Breakpoints	5/6/2013 4:28 PM	XML Document 1 KB
	custom_body_variables	3/13/2001 7:46 PM	Text Document 1 KB
	default.cfg	5/6/2013 4:27 PM	CFG File 2 KB
	default.usp	5/6/2013 4:28 PM	USP File 3 KB
	globals	5/6/2013 4:28 PM	C/C++ Header 1 KB
	lrw_custom_body	7/14/2010 6:16 PM	C/C++ Header 1 KB
	ReplaySummaryReport	5/6/2013 4:27 PM	XML Document 2 KB
	ThumbnailsCache.tmp	5/6/2013 4:30 PM	TMP File 2,591 KB
	UserTasks	5/6/2013 4:28 PM	XML Document 1 KB
	vuser_end	1/5/2012 11:52 AM	C Source 1 KB
	vuser_init	1/5/2012 11:52 AM	C Source 1 KB
	WebHttpHtml1	5/6/2013 12:20 PM	SQL Server Compac... 128 KB
	WebHttpHtml1	5/6/2013 4:28 PM	Virtual User Test 1 KB

For details on the files that are included in the script folder, see ["Files Generated During Recording" on page 271](#).

## Create a New Script Dialog Box

This dialog box enables you to create a new Vuser script.

<b>To access</b>	Do one of the following: <ul style="list-style-type: none"><li>• <b>VuGen &gt; File &gt; New Script and Solution</b></li><li>• <b>VuGen &gt; File &gt; Add &gt; New Script</b></li><li>• Click the  button on the VuGen toolbar.</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">"How to Create or Open a Vuser Script" on page 162</a></li><li>• <a href="#">"How to Record a Vuser Script" on page 175</a></li></ul>

User interface elements are described below:

UI Element	Description													
<b>Category</b>	<p>The category identifies the type of script you would like to create:</p> <p><b>Multiple Protocols.</b> Create a script using multiple protocols.</p> <p><b>Single Protocol.</b> Create a script using the selected protocol. Single Protocol is the default category.</p>													
<b>Protocol</b>	<p>The Protocol list displays protocols based on the category you select.</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Protocol List displays...</th> </tr> </thead> <tbody> <tr> <td><b>Multiple Protocols</b></td> <td>A list of protocols with a check box to the left of each protocol. Select a check box to include the protocol in the Vuser script.</td> </tr> <tr> <td><b>Single Protocol</b></td> <td>A list of protocols. You can select one protocol.</td> </tr> <tr> <td><b>Mobile</b></td> <td>Protocols that record mobile applications.</td> </tr> <tr> <td><b>Popular</b></td> <td>The most popular protocols in use in the LoadRunner user community.</td> </tr> <tr> <td><b>Recent</b></td> <td>The protocols you have most recently used.</td> </tr> </tbody> </table>		Category	Protocol List displays...	<b>Multiple Protocols</b>	A list of protocols with a check box to the left of each protocol. Select a check box to include the protocol in the Vuser script.	<b>Single Protocol</b>	A list of protocols. You can select one protocol.	<b>Mobile</b>	Protocols that record mobile applications.	<b>Popular</b>	The most popular protocols in use in the LoadRunner user community.	<b>Recent</b>	The protocols you have most recently used.
Category	Protocol List displays...													
<b>Multiple Protocols</b>	A list of protocols with a check box to the left of each protocol. Select a check box to include the protocol in the Vuser script.													
<b>Single Protocol</b>	A list of protocols. You can select one protocol.													
<b>Mobile</b>	Protocols that record mobile applications.													
<b>Popular</b>	The most popular protocols in use in the LoadRunner user community.													
<b>Recent</b>	The protocols you have most recently used.													
<b>Filter</b>	<p>Enables you to filter the Protocol list by entering text. For example, if you type "Java" into the Filter box, the Protocol list will display only those protocols that include the word Java.</p>													
<b>Script Name</b>	<p>Enables you to specify the name of your script.</p> <p>If you create a single protocol script, the default name is &lt;protocol_name&gt;x where x represents the numerical sequence of the script created. For example, the name of the third script created for the Web- HTTP/HTML protocol would be WebHttpHtml3.</p> <p>If you create a multi-protocol script, the default name is &lt;protocol_name_multi&gt;x where protocol name is the first protocol you selected from the list and x represents the numerical sequence of the script created.</p>													
<b>Location</b>	<p>Enables you specify the file location of your script. You can use the browse button to navigate to a location on your file system.</p> <p><b>Tools &gt; General &gt; Projects and Solutions</b> enables you to specify a default location.</p>													
<b>Solution Name</b>	<p>This option is displayed only when a solution is not open in the Solution Explorer. You can specify a name for the solution. If you leave it blank, the default name is 'Untitled'.</p>													

, continued

<b>Create a folder for this solution</b>	Enables you to create a folder for your solution.
<b>Solution Target</b>	Displays the file path of the solution.
<b>Protocol Advisor</b>	Enables you to access the Protocol Advisor dialog box. For details, see " <a href="#">Protocol Advisor Dialog Box</a> " on page 150
	Displays the protocols in list view.
	Displays the protocols in icon view.

## How to Work with .zip Files

VuGen allows you to work with .zip file in several ways. The advantages of working with .zip files is that you conserve disk space, and it allows your scripts to be portable. Instead of copying many files from machine to machine, you need to copy only one .zip file.

### Import from a Zip File

To open a script stored in a .zip file, select **File > Manage Zip Files > Import from Zip File**. After you select a .zip file, VuGen prompts you for a location in which to store the unzipped files.

### Export to a Zip File

To save the entire script folder as a .zip file, select **File > Manage Zip Files > Export to Zip File**.

You can indicate whether to save all the files or only the runtime files.

### Zip and Email

To create a .zip file and send it as an email attachment, select **File > Manage Zip Files > Zip and Email**. When you click **OK** in the **Zip and Email** dialog box, VuGen compresses the file according to your settings and opens an email compose form with the .zip file as an attachment.

### Edit Script in Zip File

To work from a .zip file, while not expanding or saving the script files, select **File > Manage Zip Files > Edit Script in Zip File**. When you modify the script and save it, the changes are stored directly in the .zip file.

## Vuser Script Templates

The User-Defined Template enables you to save a script with a specific configuration as a template. You can then use this template as a basis for creating future scripts.

The template supports the following files and data:

- Run-time settings
- Parameters
- Extra files
- Actions
- Snapshots

Recording options and General options are not supported as they are generic settings and are not relevant to a specific script.

## Notes and Limitations

- Once you have configured a script for a specific protocol and then save the script as a template, further scripts based on that template will only work with that same protocol.
- Once you have created your template, you cannot edit it directly in VuGen. To make any changes, you open the template and save it again with another name or overwrite the existing template.
- If you regenerate an original script from a template, you will lose all of your manual changes.

# How to Create and Open Vuser Script Templates

This task describes how to create, create from, and rename Vuser script templates.

## Create a Vuser Script Template

1. Open a script in VuGen.
2. Select **File > User-Defined Templates > Export to Template**.
3. Enter a name and location for the template.
4. Click **OK** to create the template.

## Create a Vuser Script From a Template

Select **File > New Script and Solution > VuGen > User Templates** and select the template file.

## Rename a Vuser Script Template

1. Select **File > User-Defined Templates > Manage from Explorer**
2. In the Explorer dialog box:

- a. Rename the content file (.zip)
  - b. Rename the description file (.xpt)
3. Using a text editor, modify the following tags in the .xpt file:
    - a. **Name tag:** <Name>*NewName* </Name>
    - b. **File tag src property:** <File name="template\_temp.zip" src="NewName.zip" binary="True" />

#### Notes and Limitations


- Once you have configured a script for a specific protocol and then saved the script as a template, further scripts based on that template will only work with that same protocol.
- Once you have created your template, you cannot edit it directly in VuGen. To make any changes, you open the template and save it again with another name or overwrite the existing template.

## Recording a Vuser Script

The **Recording a Vuser Script** section describes script sections, script recording, working with templates, and other recording tools.

## Recording - Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the second step, recording a Vuser script.



After you create an empty Vuser script, you are ready to use VuGen to record typical user-actions into the script. While you record the script, VuGen's floating Recording toolbar gives you access to the main recording functionality, such as pausing and stopping the recording, and inserting transactions and rendezvous points. For details on how to record a Vuser script, see ["How to Record a Vuser Script" on the next page](#).

Each Vuser script contains at least three sections: `vuser_init`, one or more action sections, and `vuser_end`. When you run multiple iterations of a Vuser script, only the *Actions* sections of the script are repeated—the `vuser_init` and `vuser_end` sections are not repeated. Before you record, and during recording, you can select the section of the script into which VuGen will insert the recorded functions. For details on the script sections, see ["Vuser Script Sections" on page 255](#).

Before you start recording, make sure that the recording options are set correctly for the script. For more information about the recording options, see ["Recording Options" on page 176](#).

When you have finished recording the user actions, VuGen generates the Vuser script and performs various other post-recording operations. You can replay the script to make sure that it functions correctly. For details, see ["Replaying a Vuser Script" on page 316](#).

To resolve situations where you cannot install VuGen on the client machine, VuGen allows you to record scripts using a LoadRunner proxy. Proxy recording may be required with certain Linux machines, Mac OS machines, and mobile devices. For details, see ["Recording via a Proxy-Overview" on page 260](#)

After you have successfully recorded a Vuser script, you can replay the script. For details, see ["Replaying - Overview" on page 316](#).

## How to Record a Vuser Script

This task describes how to record a Vuser script.

1. Create a new script or open an existing script

For details, see ["How to Create or Open a Vuser Script" on page 162](#).

2. Modify the Windows DEP settings - recommended

a. Open **Start > Control Panel > System**.

b. In the Advanced tab, click **Performance settings**.

c. In the Performance Options Data Execution Prevention tab, select the first option, **DEP for essential services only**.

If you cannot change this option, click **Add**. Browse to the client program, for example IEXPLORE.EXE.

- d. If neither of these options are possible, try to disable DEP completely.

i. Open a command prompt.

ii. Run the following command: **bcdedit.exe /set {current} nx AlwaysOff**

iii. Reboot the machine

iv. Verify that the settings took effect by running the following at the command line:  
**BCDEdit /enum**

v. Verify that the last line shows **nx AlwaysOff**.

3. Close all instances of the browser - for Web HTTP/HTML recording of Chrome or Firefox

This applies only when recording in Chrome or Firefox. You should also verify that there are no Chrome or Firefox processes running in the Task Manager.

4. **Configure the recording options - optional**

The recording options contain options that affect the way that a Vuser script is generated after recording or regenerating the script. For concept and user interface details, see "[Recording Options](#)" below.

**Tip:** If the business process you want to record contains asynchronous push communication, select **Recording Options > HTTP > Advanced Node** and check the **Use streaming mode when recording with the LoadRunner Proxy** option.

If you are not able to successfully record a script with VuGen, select **Recording Options > HTTP > Advanced Node** and check the **Use LR Proxy to record a local application** option. Then rerecord your business process.

## 5. Start the recording session

To start recording, click the **Record** button  on the VuGen toolbar, make the relevant selections in the Start Recording dialog box, and click **Start Recording**. VuGen's floating toolbar appears, VuGen opens your application and begins recording your actions.

- For user interface details, see "[Start Recording Dialog Box](#)" on page 266.
- For details on the script sections into which you can record, see "["Vuser Script Sections"](#) on page 255.

## 6. Perform a business processes on your application

Perform the desired business processes that you wish to record. The floating toolbar allows you to insert transactions, rendezvous points, and comments. You can also use the floating toolbar to specify into which section of the script to record. For user interface details, see "[Floating Recording Toolbar](#)" on page 269.

Click the **Stop** button  on the floating toolbar when you are finished recording.

**Note:** If you want to cancel the recording session, click the **Cancel Recording** button  on the floating toolbar. When you cancel a recording, VuGen removes all the code that was added to the script during the current recording session, thereby restoring the script to its status before the current recording session. For details on how to enable or disable the **Cancel Recording** button, see "["Scripting Options"](#) on page 103.

# Recording Options

The **Recording Options** sections describes the many different options that affect your Vuser script during the recording and generation stages of creating a script.

## Citrix > Configuration Node

Enables you to set the window properties and encryption settings for the Citrix client during the recording session.

To access	VuGen > Record > Recording Options > Citrix > Configuration
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
Encryption Level	The level of encryption for the ICA connection: <b>Basic</b> , <b>128 bit for login only</b> , <b>40 bit</b> , <b>56 bit</b> , <b>128 bit</b> , or <b>Use Server Default</b> to use the machine's default.
Window Size	The size of the client window. <b>Default value:</b> 800 x 600.

## Citrix > Code Generation

Enables you to configure the way VuGen captures information during recording.

To access	VuGen > Record > Recording Options > Citrix > Code Generation
Important information	<ul style="list-style-type: none"><li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on page 246.</li><li>Text synchronization steps that you add manually during the recording are not affected by the above settings—they appear in the script even if you disable the above options.</li><li>The synchronization options also work for regenerating a script. For example, if you originally recorded a script with <b>Add text synchronization calls</b> disabled, you can regenerate after recording to include text synchronization.</li></ul>

User interface elements are described below:

UI Element	Description
<b>Use Citrix Agent input in Code Generation</b>	<p>Use the Citrix Agent input to generate a more descriptive script with additional synchronization functions.</p> <p><b>Default value:</b> enabled.</p> <ul style="list-style-type: none"><li>• <b>Automatically generate text synchronization calls.</b> Adds text synchronization <b>Sync on Text</b> steps before each mouse click.</li></ul> <p><b>Default value:</b> disabled.</p>

## Citrix > Login Node

Enables you to set the connection and login information for the recording session.

To access	VuGen > Record > Recording Options > Citrix > Login
<b>Important information</b>	<ul style="list-style-type: none"><li>• This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 246</a>.</li><li>• If you do not provide login information, you are prompted for the information when the client locates the specified server.</li></ul>

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Connection</b>	<ul style="list-style-type: none"><li><b>Network Protocol.</b> The preferred protocols are TCP/IP and TCP/IP+HTTP. Most Citrix Servers support TCP/IP, however Citrix Clients starting with 11.2 do not. Certain servers, however, are configured by the administrators to allow only TCP/IP with specific HTTP headers. If you encounter a communication problem, select the TCP/IP+HTTP option.</li><li><b>Server.</b> The Citrix server name. To add a new server to the list, click <b>Add</b>, and enter the server name (and its port for TCP/IP + HTTP).</li></ul> <p><b>Note:</b> Multiple servers apply only when you specify a Published Application. If you are connecting to the desktop without a specific application, then list only one server.</p> <ul style="list-style-type: none"><li><b>Published Application.</b> The name of the <b>Published Application</b> as it is recognized on Citrix server. The drop-down menu contains a list of the available applications. If you do not specify a published application, VuGen uses the server's desktop. If you added or renamed a published application, close the Recording options and reopen them to view the new list. Additionally, you can also enter the name of a published application manually if you know it exists (useful in cases where the drop-down list is inaccurate).  To change the name of the published application on the Citrix client, you must make the change on the Citrix Server machine. Select <b>Manage Console &gt; Application</b> and create a new application or rename an existing one.  <b>Note:</b> If you do not specify a published application, Citrix load balancing will not work. To use load balancing when accessing the server's desktop, register the desktop as a published application on the server machine, and select this name from the Published Application drop-down list.</li></ul>
<b>Define connection parameters</b>	Allows you to manually define the logon and connection details.
<b>Logon Information</b>	Specify the <b>User Name</b> , <b>Password</b> , and <b>Domain</b> of the citrix user. Optionally, you can also specify the <b>Client Name</b> by which the MetaFrame server identifies the client.
<b>Use ICA file for connection parameters</b>	Specify an ICA file with the log configuration information.

## Citrix > Recorder Node

Enables you to specify how to generate window names where the window titles change during recording. You can also specify whether to save snapshots of the screens together with the script

files and whether to generate text synchronization functions.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Citrix &gt; Recorder</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Save snapshots</b>	Saves a snapshot of the Citrix client window for each script step, when relevant. We recommend that you enable this option to provide you with a better understanding of the recorded actions. Saving snapshots, however, uses more disk space and slows down the recording session.
<b>Window name</b>	In some applications, the active window name changes while you are recording. If you try to replay the script as is, the Vuser uses the original window name and the replay may fail. You can specify a naming convention for the windows in which VuGen uses a common prefix or common suffix to identify the windows as follows: <ul style="list-style-type: none"><li>• <b>Use new window name as is.</b> Set the window name as it appears in the window title. (default)</li><li>• <b>Use common prefix for new window names.</b> Use the common string from the beginning of the window titles as a window name.</li><li>• <b>Use common suffix for new window names.</b> Use the common string from the end of the window titles as a name.</li></ul> Alternatively, you can modify the window names in the actual script after recording. In the Script view, locate the window name, and replace the beginning or end of the window name with the "*" wildcard notation. <b>Example:</b> <code>ctrx_sync_on_window ("My Application*", ACTIVATE, ...CTRX_LAST);</code>

## **COM/DCOM > Filter Node**

Enables you to define which COM/DCOM objects to record.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• <b>VuGen &gt; Record &gt; Recording Options &gt; COM/DCOM &gt; Filter</b></li><li>• <b>VuGen &gt; Replay &gt; Recording Options &gt; COM/DCOM &gt; Filter</b></li></ul>
------------------	---

User interface elements are described below:

UI Element	Description
------------	-------------

<b>DCOM Profile</b>	<p><b>Specify one of the following filter types:</b></p> <ul style="list-style-type: none"><li>• <b>Default Filter.</b> The filter to be used as the default when recording a COM Vuser script.</li><li>• <b>New Filter.</b> A clean filter based on the default environment settings. Note that you must specify a name for this filter before you can record with its settings.</li></ul> <p>You can also save the current settings and delete a filter using the <b>Save As</b> and <b>Delete</b> buttons.</p>
<b>DCOM Listener Settings List</b>	<p>Displays a tree hierarchy of type libraries. You can expand the tree to show all of the available classes in the type library. You can expand the class tree to show all of the interfaces supported by that class.</p> <p>To exclude a type library, clear the check box next to the library name. This excludes all of its classes in that type library. By expanding the tree, you can exclude individual classes or interfaces by clearing the check box next to the item.</p> <p>An interface can be implemented differently by various classes. When you exclude an interface that is implemented by other classes that have not been excluded, a dialog box opens asking you if you also want to exclude the interface in all classes that implement it this interface.</p> <p>Note that when you clear the check box adjacent to an interface, it is equivalent to selecting it in the Excluded Interfaces dialog box.</p> <ul style="list-style-type: none"><li>• <b>Environment.</b> The environments to record: ADO objects, RDS Objects, and Remote Objects. Clear the objects you do not want to record.</li><li>• <b>Type Libraries.</b> A type library .tlb or .dll file, that represents the COM object to record. All COM objects have a type library that represents them. You can select a type library from the Registry, Microsoft Transaction Server, or file system.</li></ul> <p><b>Type Libraries.</b> In the lower section of the dialog box, VuGen displays the following information for each type library.</p> <ul style="list-style-type: none"><li>• <b>TypLib.</b> The name of the type library (tlb file).</li><li>• <b>Path.</b> The path of the type library.</li><li>• <b>Guid.</b> The Global Unique Identifier of the type library.</li></ul>

<b>Add</b>	<p>Adds another COM type library.</p> <ul style="list-style-type: none"><li>• <b>Browse Registry.</b> Displays a list of type libraries found in the registry of the local computer. Select the check box next to the desired library or libraries and click <b>OK</b>.</li><li>• <b>Browse file system.</b> Allows you to select type libraries from your local file system.</li><li>• <b>Browse MTS.</b> add a component from a Microsoft Transaction Server. The MTS Components dialog box prompts you to enter the name of the MTS server.  Type the name of the MTS server and click <b>Connect</b>. Remember that to record MTS components you need an MTS client installed on your machine. Select one or more packages of MTS components from the list of available packages and click <b>Add</b>. Once the package appears in the list of Type Libraries, you can select specific components from the package.</li></ul>
<b>Remove</b>	Removes a COM type library.
<b>Exclude...</b>	<p>Excludes interfaces in the filter through the Excluded Interfaces dialog box. In this dialog box, the checked interface listings are the ones that are excluded. You can also add interfaces that are not listed. Click <b>Add Interface...</b> in the Excluded Interfaces dialog box and enter the GUID number (interface ID) and name of the interface. You can copy the GUID from the interfaces.h file created by VuGen and listed in the selection tree in the left-hand column of the VuGen screen. Use the <b>Add Interface...</b> feature to exclude interfaces that are called needlessly by the script, but are not listed anywhere in the filter.</p> <p>An interface can be implemented differently by various classes. When you exclude an interface that is implemented by other classes that have not been excluded, VuGen displays a warning. If you check <b>Don't ask me again</b> and close the dialog box, then the status of all instances of the interface in all other classes will be changed automatically for this filter, whenever you change the status of the interface in one object. Click <b>Yes to all</b> to change the status of all instances of this interface for all other classes, click <b>No to all</b> to leave the status of all other instances unchanged. Click <b>Next Instance</b> to view the next class that uses this interface.</p>

## **COM/DCOM > Options Node**

Enables you to set additional options for your COM recording session, relating to the handling of objects, generation of logs, and VARIANT definitions.

The DCOM scripting options apply to all programming languages. These settings let you configure the scripting options for DCOM methods and interface handling.

**To access**


**VuGen > Record > Recording Options > COM/DCOM > Options**

User interface elements are described below:

UI Element	Description
<b>ADO Recordset filtering</b>	Condense multiple recordset operations into a single-line fetch statement (enabled by default).
<b>Declare Temporary VARIANTs as Globals</b>	Define temporary VARIANT types as Globals, not as local variables (enabled by default).
<b>Fill array in separate scopes</b>	Fill in each array in a separate scope (enabled by default).
<b>Fill structure in separate scopes</b>	Fill in each structure in a separate scope (enabled by default).
<b>Generate COM exceptions</b>	Generate COM functions and methods that raised exceptions during recording (disabled by default).
<b>Generate COM statistics</b>	Generate recording time performance statistics and summary information (disabled by default).
<b>Limit size of SafeArray log</b>	Limit the number of elements printed in the safearray log per COM call, to 16 (enabled by default).
<b>Release COM Objects</b>	Record the releasing of COM objects when they are no longer in use (enabled by default).
<b>Save Recordset content</b>	Stores Recordset content as grids, to allow viewing of recordset in VuGen (enabled by default).
<b>Trap binded moniker objects</b>	Trap all of the bound moniker objects (disabled by default).

## Correlations > Configuration

This pane enables you to configure settings for the Correlation tab.

<b>UI example</b>	
<b>To access</b>	<p>VuGen &gt; Recording Options &gt; Correlations &gt; Configuration</p>
<b>Important information</b>	<ul style="list-style-type: none"><li>"Correlation Tab [Design Studio] Overview" on page 275</li><li>"Correlations &gt; Rules" on page 186</li><li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "Protocol Compatibility Table" on page 246.</li></ul>

<b>Relevant tasks</b>	"How to Correlate Scripts Using Design Studio" on page 280
-----------------------	--

User interface elements are described below:

UI Element	Description
<b>Scan for correlations applying:</b>	
<b>Rules Scan</b>	Apply correlation rules when performing correlation scan.  For details, see " <a href="#">Correlations &gt; Rules</a> " on the next page.
<b>Automatically correlate values found</b>	Design Studio will automatically correlate dynamic values found using the rules scan.
<b>Record Scan</b>	Scan for correlations with the record based engine.
<b>Replay Scan</b>	Scan for correlations with the replay based engine.
<b>Record and Replay scan configuration</b>	
<b>API used for correlations</b>	Select the API function to be used for correlation:  <b>Boundary based:</b> web_reg_save_param_ex  <b>Regular Expression:</b> web_reg_save_param_regexp  <b>Note:</b> If you change the API function, the changes will only take effect after a new scan.
<b>Exclude strings</b>	Enables you to enter strings that should be ignored by the record and replay scan.  For details, see " <a href="#">How to Exclude Strings from the Correlation Scan</a> " on page 308
<b>Ignore values shorter than []</b>	Enables you to define how short a dynamic value can be before it is ignored by the record or replay scan.  Default length is 4 characters.
<b>Ignore values longer than []</b>	Enables you to define how long a dynamic value can be before it is ignored by the record or replay scan.  Default length is 400 characters.
<b>Warm me if the dynamic string size is greater than 10 KB</b>	Issues a warning if you try to correlate a string whose size is 10 KB or larger.
<b>Ignore case when searching for correlation values</b>	Disable case sensitivity during correlation scan.

UI Element	Description
<b>Record scan configuration</b>	
<b>Heuristic level</b>	<p>Enables you to set the filter level that controls the amount of correlation results that are returned. The higher the filter level, the shorter the scan will take to run.</p> <p><b>High.</b> Design Studio performs a detailed scan returning a highly refined result set.</p> <p><b>Medium.</b> Design Studio performs a less detailed scan returning more results. This is the default setting.</p> <p><b>Low.</b> Design Studio performs a more detailed scan returning the most results. This setting may produce many unwanted results.</p>
<b>Replay scan configuration</b>	
<b>Scan for differences between snapshots using</b>	Select a comparison method: <ul style="list-style-type: none"><li>• <b>HTML Comparison.</b> Display the differences in HTML code only.</li><li>• <b>Text Comparison.</b> Display all text, HTML, and binary differences.</li></ul>

## **Correlations > Rules**

This dialog box enables you to manage correlation rules that automatically correlate dynamic values during code generation. You can:

- Add a new application
- Add a new rule
- Delete a rule
- Export rules
- Import rules
- Test a rule

<b>To access</b>	Do one of the following: <ul style="list-style-type: none"><li>• <b>VuGen &gt; Record &gt; Recording Options &gt; Correlations &gt; Rules</b></li><li>•  <b>Studio &gt; Correlations &gt; Rules</b></li></ul>
<b>Important information</b>	"Correlation Overview" on page 274 "Correlation Tab [Design Studio] Overview" on page 275
<b>Relevant tasks</b>	"How to Correlate Scripts Using Design Studio" on page 280

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 <b>&lt;Application List &gt;</b>	A list of applications and their rules. <ul style="list-style-type: none"><li>• Select the check box adjacent to the application to activate it during recording.</li><li>• Expand the application tree to select the check box adjacent to the rules to activate them during recording.</li></ul>
 <b>New Application</b>	Add a new application to <b>&lt;Application List&gt;</b> .
 <b>New Rule</b>	Enter a new rule for the selected application in Correlation Rules. For details, see " <a href="#">"New Rule Pane" below</a> ".
 <b>Delete</b>	Delete the selected application or rule from the list.
 <b>Import...</b>	Import a file containing correlation rule definitions.
 <b>Export...</b>	Export a file containing a correlation rule definition.
 <b>Test...</b>	Test a correlation rule. For details, see " <a href="#">"Token Substitution Testpad Dialog Box" on page 189</a> ".

## New Rule Pane

Enables you to define a new custom rule.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Correlation &gt; Rules &gt; New Rule</b>
<b>Important information</b>	This pane is available only for specific protocols. For a complete list of protocols and their associated nodes, see the " <a href="#">"Protocol Compatibility Table" on page 246</a> ".

User interface elements are described below:

UI Element	Description
<b>Advanced...</b>	Opens the "Advanced Correlation Properties Dialog Box" on the next page.
<b>Action</b>	<p>Specify the type of action for the rule from the following options:</p> <ul style="list-style-type: none"> <li><b>Search for Parameters in all of the Body Text.</b> Searches the entire body—not just links, form actions or cookies. It searches the text for a match using the borders that you specify.</li> <li><b>Search for parameters inlinks and form actions.</b> Searches within links and forms' actions for the text to parameterize. This method is for application servers where you know the context rules. You define a left boundary, a right boundary, an alternate right boundary, and an instance of the left boundary within the current link.</li> <li><b>Search for Parameters from cookie headers.</b> Similar to the previous rule, except that the value is extracted from cookie text (exactly as it appears in the recording log) instead of from a link or form action.</li> <li><b>Parameterize form field value.</b> Saves the named form field value to a parameter. It creates a parameter and places it in the script before the form's action step. For this option, you need to specify the field name.</li> <li><b>Text to enter a web_reg_add_cookie function by</b> method inserts a <code>web_reg_add_cookie</code> function if it detects a certain string in the buffer. It only adds the function for those cookies with the specified prefix. For this option, you need to specify the search text and the cookie prefix.</li> </ul>
<b>Scan Type</b>	Specify the scan type either regular expression or boundary based.
<b>RegExp String</b>	Specify the regular expression. This element only applies to a regular expression scan type.
<b>Left boundary</b>	The left-most boundary where the rule will apply. This element only applies to boundary based scan type.
<b>Match Case</b>	Matches the case when looking for boundaries.
<b>Parameter prefix</b>	Uses a prefix in all automatically generated parameters based on this rule. Prefixes prevent you from overwriting existing user parameters. In addition, prefixes allow you to recognize the parameter in your script. For example, in Siebel Web, one of the built-in rules searches for the <code>Siebel_row_id</code> prefix.
<b>Right boundary</b>	The right-most boundary where the rule will apply. Use the drop-down menu to define this boundary as either the end of a string, a newline character, or a user-defined text. The element only applies to boundary based scan type.

<b>Use '#' for any digit</b>	Replaces all digits with a hash sign. The hash signs serve as wildcard, allowing you to find text strings with any digit. <b>Example:</b> If you enable this option and specify <b>HP###</b> as the left boundary, <b>HP193</b> and <b>HP284</b> will be valid matches.  This element only applies to boundary based scan type.
------------------------------	--

## ***Advanced Correlation Properties Dialog Box***

Enables you to set the advanced options for correlation rules.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Correlation &gt; Rules &gt; New Rule &gt; Advanced</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see the " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Alternate right boundary</b>	Alternative criteria for the right boundary, if the previously specified boundary is not found. Select one of the following options: <b>User-defined Text, Newline Character, End Of Page</b> .
<b>Always create new parameter</b>	Creates a new parameter for this rule even if the value replaced by the parameter has not changed from the previous instance.
<b>Left boundary instance</b>	The number of occurrences of the left boundary in order for it to be considered a match.
<b>Length</b>	The length of the string, starting with the offset, to save to the parameter. If this is not specified, the parameter continues until the end of the found value.
<b>Offset</b>	The offset of the string within the found value.
<b>Replace with parameter only for exact matches</b>	Replaces a value with a parameter only when the text exactly matches the found value.
<b>Reverse search</b>	Performs a backwards search.

## ***Token Substitution Testpad Dialog Box***

Enables you to test correlation rules before applying them.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Correlations &gt; Rules &gt; Test</b>
------------------	--

User interface elements are described below:


UI Element	Description
 Test...	Runs the test.
<b>Applied rules</b>	A list of the rules that were applied during the test.
<b>Source string for substitution</b>	Enter the source string for substitution.
<b>Substitution Result</b>	The results of the test.

## Database > Database Node

Enables you to set the recording options for database protocols.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Database &gt; Database</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
 Advanced...	Opens the " <a href="#">Database &gt; Advanced Recording Options Dialog Box</a> " below.
<b>Automatic transactions</b>	Marks every <b>Ird_exec</b> and <b>Ird_fetch</b> function as a transaction. When these options are enabled, VuGen inserts <b>Ir_start_transaction</b> and <b>Ir_end_transaction</b> functions around every <b>Ird_exec</b> or <b>Ird_fetch</b> function. <b>Default value:</b> Disabled.
<b>Script options</b>	Generates comments into recorded scripts, describing the <b>Ird_stmt</b> option values. In addition, you can specify the maximum length of a line in the script. <b>Default value:</b> 80 characters.
<b>Think time</b>	VuGen automatically records the operator's think time. You can set a threshold level, below which the recorded think time will be ignored. If the recorded think time exceeds the threshold level, VuGen places an <b>Ir_think_time</b> statement before LRD functions. If the recorded think time is below the threshold level, an <b>Ir_think_time</b> statement is not generated. <b>Default value:</b> five seconds.

## Database > Advanced Recording Options Dialog Box

Enables you set the advanced recording options for database protocols.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Database &gt; Advanced</b>
------------------	---

<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
------------------------------	--

User interface elements are described below:

UI Element	Description
<b>Code generation buffer size</b>	Specify in kilobytes the maximum size of the code generation buffer. <b>Default value:</b> 128 kilobytes.
<b>CtLib Function</b>	You can instruct VuGen to generate a send data time stamp or an extended result set statement. <ul style="list-style-type: none"> <li><b>Generate send data time stamp.</b> Generates <code>Ird_send_data</code> statements with the <code>TotalLen</code> and <code>Log</code> keywords for the <code>mpsReqSpec</code> parameter. The Advanced Recording Options dialog box lets you instruct VuGen to also generate the <code>TimeStamp</code> keyword. If you change this setting on an existing script, you must regenerate the Vuser script by choosing <b>Record &gt; Regenerate Script</b>. It is not recommended to generate the <code>Timestamp</code> keyword by default. The timestamp generated during recording is different than that generated during replay and script execution will fail. You should use this option only after a failed attempt in running a script, where an <code>Ird_result_set</code> following an <code>Ird_send_data</code> fails. The generated timestamp can be correlated with a timestamp generated by an earlier <code>Ird_send_data</code>.</li> <li><b>Generate extended result set statement.</b> Generates an <code>Ird_result_set</code> function when preparing the result set. This setting instructs VuGen to generate the extended form of the <code>Ird_result_set</code> function, <code>Ird_result_set_ext</code>. In addition to preparing a result set, this function also issues a return code and type from <code>ct_results</code>.</li> </ul>
<b>Recording engine</b>	You can instruct VuGen to record scripts with the older LRD recording engine for compatibility with previous versions of VuGen. <b>Note:</b> This option is available only for single-protocol scripts.
<b>Recording log options</b>	You can set the detail level for the trace and ASCII log files. The available levels for the trace file are <b>Off</b> , <b>Error Trace</b> , <b>Brief Trace</b> , or <b>Full Trace</b> . The error trace only logs error messages. The Brief Trace logs errors and lists the functions generated during recording. The Full Trace logs all messages, notifications, and warnings. You can also instruct VuGen to generate ASCII type logs of the recording session. The available levels are <b>Off</b> , <b>Brief detail</b> , and <b>Full detail</b> . The Brief detail logs all of the functions, and the Full detail logs all of the generated functions and messages in ASCII code.

## **Data Format Extension > Chain Configuration Node**

Enables you to add, delete, and modify chains, and to manage the DFEs that are included in the chains.

<b>To access</b>	Do one of the following: <ul style="list-style-type: none"><li>• <b>VuGen &gt; Record &gt; Recording Options &gt; Data Format Extension &gt; Chain Configuration</b></li><li>• <b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Data Format Extensions &gt; Code Generation</b></li></ul>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>See also</b>	<ul style="list-style-type: none"> <li>• "<a href="#">Data Format Extensions (DFEs) - Overview</a>" on page 831</li> <li>• "<a href="#">Data Format Extension List</a>" on page 839</li> </ul>


User interface elements are described below:

UI Element	Description
<b>Chains pane</b>	Displays a list of the DFE chains that are defined for the script.
	<b>Add Chain.</b> Enables you to add a new chain.
	<b>Edit Chain Name.</b> Enables you to modify the name of the selected chain.
	<b>Delete Chain.</b> Deletes the selected chain.
<b>Chain: &lt;chain name&gt; pane</b>	
	<b>Add DFE.</b> Enables you to add a DFE to the selected chain in the <b>Chains</b> pane. For more information on Data Format Extensions, see " <a href="#">Data Format Extension List</a> " on page 839.
	<b>Edit DFE.</b> If you selected a Prefix/Postfix Extension, you can edit the details in the <b>Add Prefix/Postfix to Chain</b> dialog box. For more information on the dialog box, see " <a href="#">Add Prefix/Postfix to Chain Dialog Box</a> " on the next page.
	<b>Delete DFE.</b> Deletes the selected DFE from the chain.
	<b>Move Up/Down.</b> Moves the selected Data Format Extension up or down in the chain. Extensions are run in the order in which they appear in the extensions list.
<b>Name</b>	The display name of the Data Format Extension.
<b>Tag</b>	The unique ID of the extension.
<b>Provider</b>	The creator of the Data Format Extension.

<b>Continue Processing</b>	Determines how the chain behaves after the DFE is applied: <ul style="list-style-type: none"><li>• <b>True:</b> The data is passed on to the next DFE in the chain, whether or not the data was converted.</li><li>• <b>False:</b> If the DFE converted the data that it received, the chain is terminated - no further DFEs are applied to the data.  If the DFE did not convert the data that it received, the data is passed on to the next DFE in the chain.</li></ul> <p><b>Note:</b> If the chain contains only a single DFE, the <b>Continue Processing</b> setting is not significant.</p>
----------------------------	--

## Add Prefix/Postfix to Chain Dialog Box

This dialog enables you to add or edit a prefix/postfix extension to the selected chain.



<b>To access</b>	<ol style="list-style-type: none"><li>1. Go to <b>Record &gt; Recording Options &gt; Data Format Extension &gt; Chain Configuration</b> node.</li><li>2. In the <b>Chain: &lt;Chain name&gt;</b> area, click the  button.</li><li>3. Select <b>Prefix Postfix Extension</b> and click <b>OK</b>.</li></ol>
------------------	--

<b>See also</b>	<a href="#">"Data Format Extension &gt; Chain Configuration Node" on page 191</a> <a href="#">"Data Format Extensions (DFEs) - Overview" on page 831</a> <a href="#">"Data Format Extension List" on page 839</a>
-----------------	---

User interface elements are described below:

UI Element	Description
<b>Case sensitive</b>	Sets the extension to cut from the defined prefix and postfix of the string only if the letter cases match.
<b>Display name</b>	The name of Prefix/Postfix Extension.
<b>Postfix to cut</b>	The section you want to cut, from the end of the string.
<b>Prefix to cut</b>	The section you want to cut, from the beginning of the string.
<b>Tag name</b>	The unique ID of the Prefix/Postfix Extension.

## Add Data Format Extension

This dialog box enables you to select the data format extension type.

<b>UI example</b>	
<b>To access</b>	VuGen > Recording Options > Data Format Extension > Chain Configuration > 
<b>Important information</b>	<ul style="list-style-type: none"><li><a href="#">"Data Format Extension &gt; Chain Configuration Node" on page 191</a></li><li><a href="#">"Add Prefix/Postfix to Chain Dialog Box" on the previous page</a></li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Apply DFE Chains to Sections of the HTTP Message" on page 837</a>
<b>Data Format Extension</b>	<b>Description</b>
Base64 Extension	Decodes strings that are encoded with a Base64 encoder.
GWT Extension	Transforms GWT data to XML format.

URL Encoding Extension	Decodes strings that are encoded with URL encoding format.
JSON to XML Extension	Transforms JSON data to XML format.
XML Extension	Receives data and checks to see if it conforms with XML syntax. This check allows VuGen to perform correlations based on XPath and to display snapshot data in an XML viewer.
Prefix Postfix Extension	Enables you to cut data from the beginning and/or end of a string which you do not want decoded. You can add and customize as many prefix/postfix extensions as required. Each postfix/prefix extension created should have a unique display name and tag name.
Binary to XML Extension	Transforms Microsoft WCF binary XML into XML format.
Remedy to XML Extension	Transforms Remedy request data into XML format.  Note that this extension does not transform Remedy response data - which is JavaScript code.
XSS Extension	Enables you to test sites that use Cross Site Scripting (XSS) defense code.

## **Data Format Extension > Code Generation Node**

Enables Data Format Extensions during code generation, and enables you to define chains for each section of the HTTP message.

To access	<b>VuGen &gt; Record &gt; Recording Options &gt; Data Format Extension &gt; Code Generation</b>
Important information	This node is available for specific protocols only. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
See also	<ul style="list-style-type: none"> <li>• <a href="#">"Data Format Extensions (DFEs) - Overview"</a> on page 831</li> <li>• <a href="#">"Data Format Extension List"</a> on page 839</li> </ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
Enable data format extension	Enables you to select chains for each message section of the HTTP message. By default, this option is not selected.

Configuration	
Format	<ul style="list-style-type: none"> <li>• <b>Code and snapshots.</b> (default) Enables Data Format Extensions on the code and snapshot data.</li> <li>• <b>Snapshots.</b> Enables Data Format Extensions on snapshot data, but does not format the data in the script itself.</li> </ul>
Verify formatted data	<p>Checks the results of the formatted data by converting it back to the original state and verifying that it matches the original data.</p> <p><b>Note:</b> Available for Base64 extension only.</p>
Chain Assignment	
 Import	Imports the Data Format Extensions from a file.
 Export	Exports the Data Format Extensions to a file.
<Message sections list>	<p>Displays a list of the following sections of the HTTP message included in the script:</p> <ul style="list-style-type: none"> <li>• Body</li> <li>• Headers</li> <li>• Cookies</li> <li>• Query String</li> </ul> <p>When you select a message section from the list, the title of the section chains pane (described below) reflects your selection and the pane displays the list of chains for that section.</p>
<Section Chains>	
	<p><b>Add Chain.</b> Adds chain to selected message section.</p> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>• Enabled for Headers and Cookies sections only. Enables you to add additional chains to the selected message section.</li> <li>• For VuGen to correctly match the chain to the Headers or Cookies section, the name in the <b>Name</b> column must match the name of the Headers or Cookies section.</li> </ul>
	<p><b>Delete Chain.</b> Removes chain from corresponding message section.</p> <p><b>Note:</b> You cannot delete the default options from any of the message sections.</p>
	<b>Reset.</b> Clears the selected chain in the Chain column.

## Flex > RTMP Node

This node enables you to include the flex\_rtmp\_receive\_stream step in Flex RTMP scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Flex &gt; RTMP</b>
<b>Important Information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Generate flex_rtmp_receive_stream step</b>	Generates a single step when recording a stream. This step does not replay certain actions, such as pause and seek. If your script requires these actions, clear the check box to record all receive and send steps. However, in this case, you must manually modify your script as described in the <i>Readme</i> .

## Flex > Configuration Node (Recording)

Enables you to set an external JVM (Java Virtual Machine) path.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Flex &gt; Configuration</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Use External JVM</b>	Enables you to use an external JVM. If you choose this option, you must specify the path:  <b>External JVM Path</b> The full path of the external JVM.  VuGen must be restarted for the changes to be applied.
<b>UseGraniteDS configuration</b>	Defines the server side Data Service configuration.  If you select this option, do not select <b>Use Flex LCDS/BlazeDS jars</b> to serialize the messages. Ensure that the granit-config.xml file matches the one deployed on the server.

<b>Maximum Formatted Request/Response size to print</b>	Enables you to specify the maximum character length of a request or response body to be captured in the log files. The option only affects the <b>flex_amf_call</b> and <b>flex_remoting_call</b> steps.  For example, if you specify a value of 1048576 characters (1MB), only responses or requests with a length less than a megabyte will be printed on the Code Generation or Replay log.
---	--

## ***Flex > Externalizable Objects Node (Recording)***

This dialog box enables you to configure how LoadRunner handles externalizable objects in Flex scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Flex &gt; Externalizable Objects</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">How to Serialize Using External Java Serializer</a></li><li>• <a href="#">"How to Serialize Flex Scripts " on page 645</a></li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Flex Overview" on page 625</a></li><li>• <a href="#">" Externalizable Objects in Flex Scripts" on page 642</a></li></ul>

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Do not serialize externalizable objects</b>	Generate script using default settings.

<b>Serialize objects using</b>	Select the appropriate option: <ul style="list-style-type: none"> <li>• Select <b>LoadRunner AMF serializer</b> if you are not using the Adobe LiveCycle Data Services or Adobe BlazeDS server.</li> <li>• Select <b>Custom Java classes</b> and select one or both of the available options:           <ul style="list-style-type: none"> <li>▪ Select <b>Use Flex LCDS/BlazeDS jars</b> if you are using Flex LCDS or BlazeDS jars to serialize the messages. If you selected <b>UseGraniteDS configuration</b> in the <b>Configuration</b> node, do not select <b>Use Flex LCDS/BlazeDS jars</b>.</li> <li>▪ Select <b>Use additional jars</b> to add additional jars to serialize the messages. You must copy the jar files from the server and specify their location in the <b>Classpath Entries</b> list described below. Copy only those jars that contain the class that is externalizable. Ensure that the files exist in the same location on all load generator computers. If you add jars with the same names as the Flex LCDS or Blaze DS jars chosen by selecting the first check box, these files will be overwritten.</li> </ul> </li> </ul>
<b>Classpath Entries List</b>	
	<b>Down Arrow.</b> Moves a classpath entry down the list.
	<b>Up Arrow.</b> Moves a classpath entry up the list.
 + Add	<b>Add Classpath.</b> Adds a new line to the classpath list.
	<b>Add Classpath Folder.</b> Adds all files from the folder to the classpath list.
	<b>Delete.</b> Permanently removes a classpath.

## General > Code Generation

This pane of the Recording Options dialog box enables you to define what tasks VuGen performs automatically after generating a Vuser script.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; General &gt; Code Generation</b>
<b>Relevant tasks</b>	<a href="#">"How to Create an Asynchronous Vuser Script" on page 448</a> <a href="#">"How to Correlate Scripts Using Design Studio" on page 280</a>

User interface elements are described below:

UI Element	Description
Correlations Scan	Instructs VuGen to analyze the Vuser script to locate dynamic values that may need to be correlated. This scan is performed after a new script is recorded and after an existing script is regenerated.
Async Scan	Instructs VuGen to analyze the Vuser script to locate asynchronous communication. This scan is performed after a new script is generated and after an existing script is regenerated.
Async Options...	Opens the <a href="#">"Asynchronous Options Dialog Box" on page 473</a> .

## General > Protocol Node

Enables you to set the script generation preferences by setting the scripting language and options.

To access	<b>VuGen &gt; Record &gt; Recording Options &gt; General &gt; Protocols</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see <a href="#">"Protocol Compatibility Table" on page 246</a> .

User interface elements are described below:

UI Element	Description
Active Protocols List	A list of the protocols which comprise your multiple protocol script. VuGen lets you modify the protocol list for which to generate code during the recording session. Select the check boxes adjacent to the protocols you want to record in the next recording session. Clear the check boxes adjacent to the protocols you do not want to record in the next recording session.

## General > Recording Node

Enables you to specify what information to record and which functions to use when generating a Vuser script, by selecting a recording level.

To access	<b>VuGen &gt; Record &gt; Recording Options &gt; General &gt; Recording</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see <a href="#">"Protocol Compatibility Table" on page 246</a> .

User interface elements are described below:

UI Element	Description

<b>HTML Advanced...</b>	Opens the "Advanced HTML Dialog Box" on the next page.
<b>URL Advanced...</b>	Opens the "Advanced URL Dialog Box" below.
<b>HTML-based script</b>	This is the default recording level for Web (HTTP/HTML) Vusers. It instructs VuGen to record HTML actions in the context of the current Web page. It does not record all resources during the recording session, but downloads them during replay. This option is recommended for browser applications with applets and VB script.
<b>URL-based script</b>	Records all requests and resources from the server. It automatically records every HTTP resource as URL steps ( <b>web_url</b> statements), or in the case of forms, as <b>web_submit_data</b> . It does not generate the <b>web_link</b> , <b>web_image</b> , and <b>web_submit_form</b> functions, nor does it record frames. This option is recommended for non-browser applications.

## Advanced URL Dialog Box

Enables you to set the advanced options for scripts using the URL recording mode.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; General &gt; Recording &gt; URL Advanced</b>
<b>Important information</b>	This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page <a href="#">246</a> .

User interface elements are described below:

UI Element	Description
<b>Use Defaults</b>	Restores the default settings of this dialog box.
<b>Create concurrent groups for resources after their source HTML page</b>	Records the resources in a concurrent group (enclosed by <b>web_concurrent_start</b> and <b>web_concurrent_end</b> statements) after the URL. Resources include files such as images and <b>js</b> files. If you disable this option, the resources are listed as separate <b>web_url</b> steps, but not marked as a concurrent group.
<b>Enable EUC-Encoded Web Pages</b>	(For Japanese windows only) Instructs VuGen to use EUC encoding. For more information, see " <a href="#">EUC-Encoding (Japanese Windows only)</a> " on page <a href="#">251</a> .
<b>Use web_custom_request only</b>	Records all HTTP requests as custom requests. VuGen generates a <b>web_custom_request</b> function for all requests, regardless of their content. Recommended for non-browser applications.

## Advanced HTML Dialog Box

Enables you to set the advanced options for HTTP-based scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; General &gt; Recording &gt; HTML Advanced</b>
<b>Important information</b>	This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page <a href="#">246</a> .

User interface elements are described below:

UI Element	Description
<b>Use Defaults</b>	Restores the default settings of this dialog box.
<b>Non-HTML generated elements</b>	<p>Many Web pages contain non-HTML elements, such as applets, XML, ActiveX elements, or JavaScript. These non-HTML elements usually contain or retrieve their own resources. Using the following options, you can control how VuGen records non HTML-generated elements.</p> <ul style="list-style-type: none"><li><b>Record within the current script step.</b> Does not generate a new function for each of the non HTML-generated resources. It lists all resources as arguments of the relevant functions, such as <code>web_url</code>, <code>web_link</code>, and <code>web_submit_data</code>. The resources, arguments of the Web functions, are indicated by the <code>EXTRARES</code> flag.</li><li><b>Record in separate steps and use concurrent groups.</b> Creates a new function for each one of the non HTML-generated resources and does not include them as items in the page's functions (such as <code>web_url</code> and <code>web_link</code>). All of the <code>web_url</code> functions generated for a resource are placed in a concurrent group (surrounded by <code>web_concurrent_start</code> and <code>web_concurrent_end</code>).</li><li><b>Do not record.</b> Does not record any non-HTML generated resources.</li></ul>

Script type	<ul style="list-style-type: none"><li>• <b>A script describing user actions.</b> Generates functions that correspond directly to the action taken. It creates URL (<code>web_url</code>), link (<code>web_link</code>), image (<code>web_image</code>), and form submission (<code>web_submit_form</code>) functions. The resulting script is very intuitive and resembles a context sensitive recording.</li><li>• <b>A script containing explicit URL's only.</b> Records all links, images and URLs as <code>web_url</code> statements, or in the case of forms, as <code>web_submit_data</code>. It does not generate the <code>web_link</code>, <code>web_image</code>, and <code>web_submit_form</code> functions. The resulting script is less intuitive. This mode is useful for instances where many links within your site have the same link text. If you record the site using the first option, it records an ordinal (instance) for the link, but if you record using the second option, each link is listed by its URL. This facilitates parameterization and correlation for that step.</li></ul>
-------------	---

## General > Script Node

Enables you to set the script generation preferences by setting the scripting language and options.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; General &gt; Script</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Add a comment for each action</b>	Insert informative logging messages before each message invocation (non-C only). <b>Default value:</b> enabled.
<b>Close all AUT processes when recording stops</b>	Automatically closes all of the AUT's (Application Under Test) processes when VuGen stops recording. <b>Default value:</b> disabled.
<b>Correlate arrays</b>	Tracks and correlates arrays of all data types, such as string, structures, numbers, and so on. <b>Default value:</b> enabled.
<b>Correlate large numbers</b>	Correlates long data types such as integers, long integers, 64-bit characters, float, and double. <b>Default value:</b> disabled.
<b>Correlate simple strings</b>	Correlates simple, non-array strings and phrases. <b>Default value:</b> disabled.

UI Element	Description
<b>Correlate small numbers</b>	Correlates short data types such as bytes, characters, and short integers. <b>Default value:</b> disabled.
<b>Correlate structures</b>	Tracks and correlates complex structures. <b>Default value:</b> enabled.
<b>Declare primitives as locals</b>	Declares primitive value variables as local variables rather than class variables (C, C#, and .NET only). <b>Default value:</b> enabled.
<b>Explicit variant declaration</b>	Declares variant types explicitly in order to handle ByRef variants (Visual Basic for Applications only). <b>Default value:</b> enabled.
<b>Generate fixed think time after end transaction</b>	Adds a fixed think time, in seconds, after the end of each transaction. When you enable this option, you can specify a value for the think time. <b>Default value:</b> disabled, 3 seconds when enabled.
<b>Generate recorded events log</b>	Generates a log of all events that took place during recording. <b>Default value:</b> disabled.
<b>Generate think time greater than threshold</b>	Uses a threshold value for think time. If the recorded think time is less than the threshold, VuGen does not generate a think time statement. You also specify the threshold value. The default values is 3—if the think time is less than 3 seconds, VuGen does not generate think time statements. If you disable this option, VuGen will not generate any think times. <b>Default value:</b> enabled, 3 seconds.
<b>Insert output parameters values</b>	Inserts output parameter values after each call (C, C#, and .NET only). <b>Default value:</b> disabled.
<b>Insert post-invocation info</b>	Insert informative logging messages after each message invocation (non-C only). <b>Default value:</b> enabled.
<b>Maximum number of lines in action file</b>	Create a new file if the number of lines in the action exceeds the specified threshold. The default threshold is 60000 lines (C, C#, and .NET only). <b>Default value:</b> disabled.

UI Element	Description
<b>Replace long strings with parameter</b>	<p>Save strings exceeding the maximum length to a parameter. This option has an initial maximum length of 100 characters. The parameters and the complete strings are stored in the <b>Ir_strings.h</b> file in the script's folder in the following format:</p> <pre>const char &lt;paramName_uniqueID&gt; ="string".</pre> <p>This option allows you to have a more readable script. It does not effect the performance of the script.</p> <p><b>Default value:</b> enabled.</p>
<b>Reuse variables for primitive return values</b>	<p>Reuse the same variables for primitives received from method calls. This overrides the <b>Declare primitives as locals setting</b>.</p> <p><b>Default value:</b> enabled.</p>
<b>Track processes created as COM local servers</b>	<p>Track the activity of the recorded application if one of its sub-processes was created as a COM local server (C and COM only).</p> <p><b>Default value:</b> enabled.</p>
<b>Use full type names</b>	<p>Use the full type name when declaring a new variable (C# and .NET only).</p> <p><b>Default value:</b> disabled.</p>
<b>Use helpers for arrays</b>	<p>Use helper functions to extract components in variant arrays (Java and VB Scripting only).</p> <p><b>Default value:</b> disabled.</p>
<b>Use helpers for objects</b>	<p>Use helper functions to extract object references from variants when passed as function arguments (Java and VB Scripting only).</p> <p><b>Default value:</b> disabled.</p>
<b>Use protected application recording</b>	<p>Use this option if VuGen is unable to record your application. Your application may block access to VuGen, and recording with this option selected may enable access.</p> <p><b>Default value:</b> disabled.</p>
<b>Warn me if the application being recorded encounters an error</b>	<p>Selecting this option enables VuGen to prompt you to cancel the recording if the recorded application crashes or if no events are recorded for 3 minutes. If you choose to cancel the recording, no script is generated.</p> <p><b>Default value:</b> enabled.</p> <p><b>Note:</b> This option is available for Web (HTTP/HTML) Vuser scripts only.</p>

## GUI Properties > Web Event Configuration Node

Enables you to set the level of detail recorded in a script (web event recording).

To access	VuGen > Record > Recording Options > GUI Properties > Web Event Configuration
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
Basic Event Configuration Level	<ul style="list-style-type: none"><li>Always records click events on standard Web objects such as images, buttons, and radio buttons.</li><li>Always records the submit event within forms.</li><li>Records click events on other objects with a handler or behavior connected.</li><li>Records the mouseover event on images and image maps only if the event following the mouseover is performed on the same object.</li></ul>
Custom Settings	Opens the " <a href="#">Custom Web Event Recording Configuration Dialog Box</a> " below, where you can customize the event recording configuration.
High Event Configuration Level	In addition to the objects recorded in the <b>Medium</b> level, it records mouseover, mousedown, and double-click events on objects with handlers or behaviors attached.
Medium Event Configuration Level	In addition to the objects recorded in the <b>Basic</b> level, it records click events on the <DIV>, <SPAN>, and <TD> HTML tag objects.

## ***Custom Web Event Recording Configuration Dialog Box***

Enables you to customize the level of web event recording.

To access	VuGen > Record > Recording Options > GUI Properties > Web Event Configuration > Custom Settings
Important information	This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Object List>	A list of the web objects. Each web object can be customized according to the other settings in this dialog box.
<Object Menu>	<ul style="list-style-type: none"> <li><b>Add.</b> Adds a new HTML tag object to the object list. Type in the name of the tag.</li> <li><b>Delete.</b> Deletes an object from the object list.</li> </ul>
Event Menu	<ul style="list-style-type: none"> <li><b>Add.</b> Adds an event to the Event Name column of this object.</li> <li><b>Delete.</b> Deletes an event from the Event Name column of this object.</li> </ul>
Event Name	A list of events associated with the object.
File Menu	<ul style="list-style-type: none"> <li><b>Load Configuration.</b> Loads a previously created custom configuration.</li> <li><b>Save Configuration As.</b> Saves the current configuration.</li> </ul>
Listen	<p>The criteria which determines when VuGen listens for an event.</p> <ul style="list-style-type: none"> <li><b>Always.</b> Always listen to the event.</li> <li><b>If Handler.</b> Listens to the event if a handler is attached to it. A handler is code in a Web page, typically a function or routine written in a scripting language, that receives control when the corresponding event occurs.</li> <li><b>If Behavior.</b> Listens to the event if a DHTML behavior is attached to it. A DHTML behavior encapsulates specific functionality or behavior on a page. When applied to a standard HTML element on a page, a behavior enhances that element's default behavior.</li> <li><b>If Handler or Behavior.</b> Listens to the event if either a handler or a behavior is attached to it.</li> <li><b>Never.</b> Never listens to the event.</li> </ul> <p>For more information, see "<a href="#">Tips for Working with Event Listening and Recording</a>" on <a href="#">page 254</a>.</p>

UI Element	Description
Record	<p>The criteria which determines when VuGen records an event.</p> <ul style="list-style-type: none"> <li>• <b>Enabled.</b> Records the event each time it occurs on the object as long as VuGen listens to the event on the selected object, or on another object to which the event bubbles. Bubbling is the process whereby, when an event occurs on a child object, the event can travel up the chain of hierarchy within the HTML code until it encounters an event handler to process the event.</li> <li>• <b>Disabled.</b> Does not record the specified event and ignores event bubbling where applicable.</li> <li>• <b>Enabled on next event.</b> Same as <b>Enabled</b>, except that it records the event only if the subsequent event occurs on the same object. For example, suppose a mouseover behavior modifies an image link. You may not want to record the mouseover event each time you happen to move the mouse over this image. Because only the image that is displayed after the mouseover event enables the link event, however, it is essential that the mouseover event is recorded before a click event on the same object.</li> </ul> <p>For more information, see "<a href="#">Tips for Working with Event Listening and Recording</a>" on <a href="#">page 254</a>.</p>
Reset Settings	Resets the custom settings to the settings of your choice: <b>basic</b> , <b>medium</b> , or <b>high</b> .

## HTTP > Advanced Node

Enables you to customize the code generation settings in the area of think time, resetting contexts, saving snapshots, and the generation of **web\_reg\_find** functions.

To access	VuGen > Record > Recording Options > HTTP Properties > Advanced
Important information	<ul style="list-style-type: none"> <li>• This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 246</a>.</li> <li>• Some options within this node are not available in when using a multi-protocol script.</li> </ul>

User interface elements are described below:

UI Element	Description
	Opens the " <a href="#">Headers Dialog Box</a> " on <a href="#">page 211</a> .

<b>Content Types...</b>	Opens the "Content Type Filters Dialog Box" on page 212.
<b>Non-Resources...</b>	Opens the "Non-Resources Dialog Box" on page 212.
<b>Reset context for each action</b>	Resets all HTTP contexts between actions. Resetting contexts allows the Vuser to more accurately emulate a new user beginning a browsing session. This option resets the HTML context, so that a context-less function is always recorded in the beginning of the action. It also clears the cache and resets the user names and passwords. <b>Note:</b> This option is available only for Web and Oracle NCA protocols
<b>Save snapshot resources locally</b>	Saves a local copy of the snapshot resources during record and replay, thereby creating snapshots more accurately and displaying them quicker.
<b>Generate web_reg_find functions for page titles</b>	Generates <b>web_reg_find</b> functions for all HTML page titles. VuGen adds the string from the page's title tag and uses it as an argument for <b>web_reg_find</b> . <ul style="list-style-type: none"> <li><b>Generate web_reg_find functions for sub-frames.</b> Generates <b>web_reg_find</b> functions for page titles in all sub-frames of the recorded page.</li> </ul> <b>Note:</b> This option is available only for Web and Oracle NCA protocols
<b>Add comment to script for HTTP errors while recording</b>	Adds a comment to the script for each HTTP request error. An error request is defined as one that generated a server response value of 400 or greater during recording.
<b>Support charset</b>	<ul style="list-style-type: none"> <li><b>UTF-8.</b> Enables support for UTF-8 encoding. This instructs VuGen to convert non-ASCII UTF-8 characters to the encoding of your locale's machine in order to display them properly in VuGen. You should enable this option only on non-English UTF-8 encoded pages. The recorded site's language must match the operating system language. You cannot record non-English Web pages with different encodings (for example, UTF-8 together with ISO-8859-1 or shift_jis) within the same script.</li> <li><b>EUC-JP.</b> If you are using Japanese Windows, select this option to enable support for Web sites that use EUC-JP character encoding. This instructs VuGen to convert EUC-JP strings to the encoding of your locale's machine in order to display them properly in VuGen. VuGen converts all EUC-JP (Japanese UNIX) strings to the SJIS (Japanese Windows) encoding of your locale's machine, and adds a <b>web_sjis_to_euc_param</b> function to the script. (Kanji only)</li> </ul>

<b>Parameterize server names</b>	VuGen identifies server names and IP addresses when you regenerate a Vuser script. These server names and IP addresses are contained in specific arguments associated with specific functions in the Vuser script. [See the table below for details.] VuGen replaces the identified server names and IP addresses with parameters. Parameterizing server names and IP addresses enables you to run the Vuser script in different environments by simply changing the server and IP address values in the parameter file. For an introduction to parameters, see " <a href="#">"Parameterizing - Overview" on page 408</a> .												
<p>Note: To identify data for parameterization, VuGen searches the arguments that are listed for the following functions:</p>													
	<table border="1"><thead><tr><th>API Function</th><th>Arguments</th></tr></thead><tbody><tr><td>web_url</td><td><ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul></td></tr><tr><td>web_custom_request</td><td><ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul></td></tr><tr><td>web_image</td><td><ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul></td></tr><tr><td>web_submit_data</td><td><ul style="list-style-type: none"><li>• Action</li><li>• URL</li><li>• Referrer</li></ul></td></tr><tr><td>web_submit_form</td><td><ul style="list-style-type: none"><li>• Action</li><li>• URL</li><li>• Referrer</li></ul></td></tr></tbody></table>	API Function	Arguments	web_url	<ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul>	web_custom_request	<ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul>	web_image	<ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul>	web_submit_data	<ul style="list-style-type: none"><li>• Action</li><li>• URL</li><li>• Referrer</li></ul>	web_submit_form	<ul style="list-style-type: none"><li>• Action</li><li>• URL</li><li>• Referrer</li></ul>
API Function	Arguments												
web_url	<ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul>												
web_custom_request	<ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul>												
web_image	<ul style="list-style-type: none"><li>• URL</li><li>• Referrer</li></ul>												
web_submit_data	<ul style="list-style-type: none"><li>• Action</li><li>• URL</li><li>• Referrer</li></ul>												
web_submit_form	<ul style="list-style-type: none"><li>• Action</li><li>• URL</li><li>• Referrer</li></ul>												
	<p>By default, this option is not selected.</p>												
<b>Use the LR Proxy to record a local application</b>	Provides an alternative way to record if the standard VuGen recording mechanism is not compatible with your application. This applies when you have selected to record a Web browser or Windows application.												
<p><b>Note:</b> After recording, clear this option to restore the default mode.</p>													

<b>Use streaming mode when recording with the LoadRunner Proxy</b>	Streaming mode enables HTTP data portions received from the server to be forwarded to the application with buffering. This allows you to record asynchronous push communication.
--	--

**Note:** If this option is enabled, the remote recording toolbar is disabled.

## Headers Dialog Box

Enables you to automatically send additional HTTP headers with every HTTP request submitted to the server.

To access	VuGen > Record > Recording Options > HTTP > Advanced > Headers
<b>Important information</b>	<ul style="list-style-type: none"><li>This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 246</a>.</li><li>The following standard headers are considered risky: Authorization, Connection, Content-Length, Cookie, Host, If-Modified-Since, Proxy-Authenticate, Proxy-Authorization, Proxy-Connection, Referer, and WWW-Authenticate. They are not recorded unless selected in the Header list.</li></ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Plus.</b> Adds a new entry.
	<b>Minus.</b> Deletes an entry.
	Restores the current list to the default values and entries.
	Restores all lists to the default values and entries.
<Drop-down menu>	Controls the options for this dialog box: <ul style="list-style-type: none"><li><b>Do not record headers</b></li><li><b>Record headers in list</b></li><li><b>Record headers not in list</b></li></ul>
<Header list>	List of headers which may or may not be recorded. The lists vary depending on which drop-down item is selected. Each item can be selected or deselected using its individual check box.

## Content Type Filters Dialog Box

Enables you to filter content types for your recorded script. You can specify the type of the content you want to record or exclude from your script.

To access	<b>VuGen &gt; Record &gt; Recording Options &gt; HTTP &gt; Advanced &gt; Content Types</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Plus.</b> Adds a new entry.
	<b>Minus.</b> Deletes an entry.
	Restores the current list to the default values and entries.
	Restores all lists to the default values and entries.
<Drop-down menu>	Controls the options for this dialog box: <ul style="list-style-type: none"><li>• <b>Do not filter content types.</b></li><li>• <b>Filter content types in list.</b></li><li>• <b>Filter content types not in list.</b></li></ul>
<Header list>	List of content types which may or may not be filtered. The lists vary depending on which drop-down item is selected. Each item can be selected or deselected using its individual check box.

## Non-Resources Dialog Box

When you record a script, VuGen indicates whether or not it will retrieve the resource during replay using the Resource attribute in the **web\_url** function. If the Resource attribute is set to 0, the resource is retrieved during script execution. If the Resource attribute is set to 1, the Vuser skips the resource type.

You can exclude specific content types from being handled as resources. For example, you can indicate to VuGen that **gif** type resources should not be handled as a resource and therefore be downloaded unconditionally.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; HTTP &gt; Advanced &gt; Non-Resources</b>
<b>Important information</b>	This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page <a href="#">246</a> .

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Add.</b> Adds a new entry to the list.
	<b>Remove.</b> Deletes an entry from the list.
	Restores the default list.
<b>&lt;Non-Resource Content Type list&gt;</b>	List of items which should not be recorded as resources. Each item can be selected or deselected using its individual check box.

## ***Flex > Configuration Node (Recording)***

Enables you to set an external JVM (Java Virtual Machine) path.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options&gt; Flex &gt; Configuration</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page <a href="#">246</a> .

User interface elements are described below:

UI Element	Description
<b>Use External JVM</b>	Enables you to use an external JVM. If you choose this option, you must specify the path:  <b>External JVM Path</b> The full path of the external JVM.  VuGen must be restarted for the changes to be applied.
<b>UseGraniteDS configuration</b>	Defines the server side Data Service configuration.  If you select this option, do not select <b>Use Flex LCDS/BlazeDS jars</b> to serialize the messages. Ensure that the granit-config.xml file matches the one deployed on the server.

<b>Maximum Formatted Request/Response size to print</b>	Enables you to specify the maximum character length of a request or response body to be captured in the log files. The option only affects the <b>flex_amf_call</b> and <b>flex_remoting_call</b> steps.  For example, if you specify a value of 1048576 characters (1MB), only responses or requests with a length less than a megabyte will be printed on the Code Generation or Replay log.
---	--

## ***Flex > Externalizable Objects Node (Recording)***

This dialog box enables you to configure how LoadRunner handles externalizable objects in Flex scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Flex &gt; Externalizable Objects</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">How to Serialize Using External Java Serializer</a></li><li>• <a href="#">"How to Serialize Flex Scripts " on page 645</a></li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Flex Overview" on page 625</a></li><li>• <a href="#">" Externalizable Objects in Flex Scripts" on page 642</a></li></ul>

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Do not serialize externalizable objects</b>	Generate script using default settings.

<b>Serialize objects using</b>	Select the appropriate option: <ul style="list-style-type: none"><li>• Select <b>LoadRunner AMF serializer</b> if you are not using the Adobe LiveCycle Data Services or Adobe BlazeDS server.</li><li>• Select <b>Custom Java classes</b> and select one or both of the available options:<ul style="list-style-type: none"><li>▪ Select <b>Use Flex LCDS/BlazeDS jars</b> if you are using Flex LCDS or BlazeDS jars to serialize the messages. If you selected <b>UseGraniteDS configuration</b> in the <b>Configuration</b> node, do not select <b>Use Flex LCDS/BlazeDS jars</b>.</li><li>▪ Select <b>Use additional jars</b> to add additional jars to serialize the messages. You must copy the jar files from the server and specify their location in the <b>Classpath Entries</b> list described below. Copy only those jars that contain the class that is externalizable. Ensure that the files exist in the same location on all load generator computers. If you add jars with the same names as the Flex LCDS or Blaze DS jars chosen by selecting the first check box, these files will be overwritten.</li></ul></li></ul>
<b>Classpath Entries List</b>	
	<b>Down Arrow.</b> Moves a classpath entry down the list.
	<b>Up Arrow.</b> Moves a classpath entry up the list.
	<b>Add Classpath.</b> Adds a new line to the classpath list.
	<b>Add Classpath Folder.</b> Adds all files from the folder to the classpath list.
	<b>Delete.</b> Permanently removes a classpath.

## .NET > Filters Node

Enables you to set the recording options for .NET Vuser scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Microsoft .NET &gt; Filters</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>See also</b>	<ul style="list-style-type: none"> <li>• "<a href="#">.NET Filters Overview</a>" on page 727</li> <li>• "<a href="#">.NET Filters - Advanced</a>" on page 728</li> <li>• "<a href="#">Guidelines for Setting .NET Filters</a>" on page 729</li> </ul>

User interface elements are described below:

UI Element	Description
Create...	Opens the Create a New Filter dialog box, enabling you to create a new filter. For more details, see " <a href="#">Create a New Filter Dialog Box [.NET Protocol]</a> " below.
Filter Manager...	Opens the Filter Manager, allowing you to view and modify all Microsoft .NET protocol filters. For details, see " <a href="#">Filter Manager [.NET Protocol]</a> " below.
Custom Filter	Shows the filters that you created earlier on the current machine.
Environment Filter	Lists the available environment filters: .NET Remoting, ADO.NET, Enterprise Services, and WCF (Windows Communication Foundation of Framework 3.0).
New Filter	Indicates that you want to create a new filter.

## ***Create a New Filter Dialog Box [.NET Protocol]***

This dialog box enables you to create a new filter for .NET Vuser scripts.

To access	VuGen > Record > Recording Options > Microsoft .NET > Filters > New Filter > Create
-----------	---

User interface elements are described below:

UI Element	Description
Based on a custom filter	Create a new filter based on a custom filter. Use the drop-down menu to select the custom filter.
Based on an environment filter	Create a new filter based on an environment filter. Use the check boxes next to the environment filters to indicate which environment filters to base the filter on.
Start with an empty filter	Create a new filter that is not based on a pre-existing filter.

## ***Filter Manager [.NET Protocol]***

This dialog box enables you to create and edit .NET filters.

To access	VuGen > Record > Recording Options > Microsoft .NET > Filters > Environment / Custom Filter > Filter Manager
See also	<a href="#">".NET Filters Overview" on page 727</a> <a href="#">".NET Filters - Advanced" on page 728</a> <a href="#">"Guidelines for Setting .NET Filters" on page 729</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Includes the selected element. If you manually include a parent node, the Filter Manager includes the child elements below it, provided that no other rule exists. For example, if you include a class, it will include all its methods unless you specifically excluded a method.
	Excludes the selected element. The child elements are also excluded unless they were included by another rule. By default, when you exclude a class, the Filter Manager applies the Exclude attribute to the class, but it allows the recording engine to record activity within the methods of the excluded class. When you exclude a method, however, the Filter Manager applies Totally Exclude, preventing the recording engine from recording any activity within the methods of the excluded class. Advanced users can modify these setting in the filter file.
	<p>Removes the manual inclusion or exclusion rule. In this case, the element may be impacted by other parent elements.</p> <p>The inclusion and exclusion rules have the following properties:</p> <ul style="list-style-type: none"> <li>The rules are hierarchical—if you add an include or exclude rule to a class, then the derived classes will follow the same rule unless otherwise specified.</li> <li>A rule on a class only affects its public methods, derived classes, and inner classes.</li> <li>A rule on a namespace affects all the classes and their public methods.</li> <li>Note that adding or removing assemblies does not necessarily affect the classes that they contain—you can remove an assembly, yet its methods may be recorded due to the hierarchical nature of the filter.</li> <li>As part of the filter design, several methods, such as <b>.cctor()</b> and <b>Dispose (bool)</b>, do not follow the standard hierarchical rules.</li> </ul> <p><b>Note:</b> The resetting of a parent node does not override a manual inclusion or exclusion applied to a child node. For example, if you manually <b>exclude</b> a method, and then reset its class, which by default <b>included</b> all sub-nodes, your method will remain excluded.</p> <p>Properties and events are view-only and cannot be included or excluded through the Filter Manager. In addition, several system related elements are protected and may not be altered.</p> <p>For tips about including and excluding elements in the filter, see "<a href="#">Guidelines for Setting .NET Filters</a>" on page 729.</p>
	Navigates to the previous or next tree node visited by the user.

	<p><b>Show non-public items.</b> By default, the filter manager shows only public classes and class members. By clicking the  button, non-public items will be displayed in the tree view.</p> <p>If you include a class which contains non-public items, they will not be added to the filter automatically. You must explicitly include each non-public item to the filter.</p>
<b>Impact Log</b>	<p>The Impact Log indicates what your last changes were and how they affected your filter. The user actions are listed in descending order, with the latest changes at the top.</p> <p>For each element affected by your manual inclusion or exclusion, the log indicates how it affected the element. It also provides a link to that element in the Filter Manager.</p> <p>To view the Impact Log, click the Impact Log button on the Filter Manager's toolbar or select <b>Actions &gt; View Impact Log</b> in the Filter Manager window.</p>
<b>&lt;Filter Manager Tree&gt;</b>	<p>The Filter Manager tree uses symbols to illustrate the elements and their status. For details about each of the icons, see the table below.</p> <ul style="list-style-type: none"> <li>Element icons represent the type of element—assembly, namespace, class, method, structure, property, events, or interfaces.</li> <li>A check mark or X adjacent to the element icon, indicates whether or not the element is included or excluded.</li> <li>A bold element indicates that it was explicitly included or excluded. This may be a result of being manually included or excluded by the user or by a pre-defined rule in the environment filter. If you reset a bold node, it returns to its original, non-bold state.</li> </ul>
<b>Add Reference</b>	Opens the Add Reference dialog box with a list of .NET Framework components or assemblies in the Public Assemblies folder. For more information, see " <a href="#">Add Reference Dialog Box [.NET Protocol]</a> " on the next page.
<b>Delete</b>	Deletes the selected custom filter. The Filter Manager prompts you for a confirmation.
<b>New</b>	Opens the Create a New Filter dialog box, in which you create an empty filter or a new filter based on an existing one. For more information, see " <a href="#">Create a New Filter Dialog Box [.NET Protocol]</a> " on page 216.
<b>Remove Reference</b>	Removes the assembly that is selected in the Filter Manager and all of the elements associated with it. The Filter Manager prompts you for a confirmation.
<b>Save</b>	Saves the changes you made to filter.
<b>View Impact Log</b>	Opens the Impact log for the selected filter. The Impact log shows which nodes in the tree were affected by recent actions.

The following table shows the Filter Manager Tree icons that represent the various elements:

Icon	Description	Icon	Description
	assembly		interface
	assembly that couldn't be loaded		method
	assembly that was partially loaded		static method
	class		namespace
	constructor		property
	static constructor		static property
	event		structure
	static event		

## Add Reference Dialog Box [.NET Protocol]

This dialog box enables you to add references to .NET filters.

To access	VuGen > Record > Recording Options > Microsoft .NET > Filters > Environment / Custom Filter > Filter Manager > Add Reference
-----------	--

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>&lt;Component List&gt;</b>	A list of .NET Framework components or assemblies in the Public Assemblies folder. <ul style="list-style-type: none"> <li>To add one of the listed items, select it and click <b>Select</b>. You can select multiple components using ctrl-click. The bottom pane shows the selected references.</li> <li>To add an assembly that is not in the list, click <b>Browse</b> and locate the reference on your file system or network.</li> </ul>
<b>&lt;Selected Component List&gt;</b>	The list of selected components. The Type column indicates <b>.NET</b> for a component from the Public Assemblies folder and <b>File</b> for a component that was added by selecting <b>Browse</b> . <ul style="list-style-type: none"> <li>To clear an item from the list, select it in the bottom pane and click <b>Remove</b>.</li> </ul>

## GUI Properties > Advanced Node

Enables you to set advanced recording options for Click & Script Vusers.

To access	<b>VuGen &gt; Record &gt; Recording Options &gt; GUI Properties &gt; Advanced</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

### Recording Settings Properties

UI Element	Description
<b>Record rendering-related property values</b>	Records the values of the rendering-related properties of DOM objects (for example, <code>offsetTop</code> ), so that they can be used during replay. Note that this may significantly decrease the replay speed. <b>Default value:</b> disabled.
<b>Record 'click' by mouse events</b>	Records mouse clicks by capturing mouse events instead of capturing the <code>click()</code> method. Enable when the recorded application uses the DOM <code>click()</code> method, to prevent the generation of multiple functions for the same user action. <b>Default value:</b> enabled.
<b>Record socket level data</b>	Enables the recording of socket level data. If you disable this option you will need to manually add the starting URL before recording. In addition, you will be unable to regenerate the script on an HTML level. <b>Default value:</b> enabled.
<b>Generate snapshots for Ajax steps</b>	Enables generation of snapshots for Ajax steps. Enabling this option can result in errors during recording. <b>Default value:</b> disabled.

### Code Generation Settings Properties

UI Element	Description
<b>Enable generation of out-of-context steps</b>	Creates a URL-based script for ActiveX controls and Java applets, so that they will be replayed. Since these functions are not part of the native recording, they are referred to as out-of-context recording. <b>Default value:</b> disabled.
<b>Enable automatic browser title verification</b>	Enables automatic browser title verification. <b>Default value:</b> disabled.

, continued

Perform a title verification for	<ul style="list-style-type: none"><li><b>each navigation.</b> Performs a title verification only after a navigation. When a user performs several operations on the same page, such as filling out a multi-field form, the title remains the same and verification is not required.</li><li><b>each step.</b> Performs a title verification for each step to make sure that no step modified the browser title. A modified browser title may cause the script to fail.</li><li><b>Perform a title verification using the URL if the title is missing.</b> For browser windows without a title, perform a title verification for each step using its URL.</li></ul>
----------------------------------	--

## .NET > Recording - Recording Node

This screen enables you to set the recording options for .NET Vuser scripts.

To access	<b>VuGen &gt; Record &gt; Recording Options &gt; Microsoft .NET &gt; Recording</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
Code Generation	<p>Allow you to indicate whether to show warnings, a stack trace, or all event subscriptions during code generation.</p> <ul style="list-style-type: none"><li><b>Show Warnings.</b> Shows warning messages that are issued during the code generation process.</li><li><b>Show Stack Trace.</b> Shows the recorded stack trace if it is available.</li><li><b>Show All Event Subscriptions.</b> Generates code for all event subscriptions that were recorded. If this option is disabled, VuGen will only generate code for events in which both the publisher (the object which invokes the event) and the subscriber (the object informed of the event) are included in the filter.</li></ul> <p><b>Default value:</b> disabled.</p>

<b>Debug Options</b>	<p>Enables you to trace the stack and specify its size.</p> <ul style="list-style-type: none"><li>• <b>Stack Trace.</b> Traces the contents of the stack for each invocation within the script. It allows you to determine which classes and methods were used by your application. This can be useful in determining which references, namespaces, classes, or methods to include in your filter. Enabling the trace may affect your application's performance during recording.</li></ul> <p><b>Default value:</b> disabled.</p> <ul style="list-style-type: none"><li>• <b>Stack Trace Limit.</b> The maximum number of calls to be stored in the stack. If the number of calls exceeds the limit, VuGen truncates it.</li></ul> <p><b>Default value:</b> 20 calls.</p>
<b>Filters</b>	<ul style="list-style-type: none"><li>• <b>Ignore all assemblies by default.</b> Ignores all assemblies that are not explicitly included by the selected filter. If you disable this option, VuGen looks for a matching filter rule for all assemblies loaded during the recording.</li></ul>
<b>Logging</b>	<p>The Logging options let you set the level of detail that is recorded in the recording log file.</p> <ul style="list-style-type: none"><li>• <b>Log severity.</b> Sets the level of logging to <b>Errors Only</b> (default), or <b>Debug</b>. The severity setting applies for all the logs that you enable below. You should always use the <b>Errors Only</b> log unless specifically instructed to do otherwise by HP support, since detailed logging may significantly increase the recording time.</li><li>• <b>Instrumentation Log.</b> Logs messages related to the instrumentation process.</li></ul> <p><b>Default value:</b> enabled.</p> <ul style="list-style-type: none"><li>• <b>Recording Log.</b> Logs messages issued during recording.</li></ul> <p><b>Default value:</b> enabled.</p> <ul style="list-style-type: none"><li>• <b>Code Generation Log.</b> Logs messages issued during the code generation stage.</li></ul> <p><b>Default value:</b> enabled.</p>
<b>Remote Objects</b>	For information about this property, see <a href="#">Remote Objects Property</a> .

<b>Serialization</b>	<ul style="list-style-type: none"><li>• <b>Serialization format.</b> The format of the serialization file that VuGen creates while recording a class that supports serialization: <b>Binary</b>, <b>XML</b>, or <b>Both</b>. The advantage of the binary format is that since it is more compressed, it is quicker. The disadvantage of the binary format is that you do not have the ability to manipulate the data as you do with XML.</li><li>• <b>Serialize long arrays.</b> For long arrays containing serializable objects (for example, an array of primitives), use VuGen's serialization mechanism. Enabling this option generates <b>LrReplayUtils.GetSerializedObject</b> calls if the array size is equal to or larger than the threshold value.</li><li>• <b>Threshold value for long array size.</b> The threshold size for an array to be considered a <b>long</b> array. If the array size is equal to or larger than this size, VuGen serializes it when detecting serializable objects.</li></ul> <p><b>Tip:</b> For XML serialization, you can view the content of the XML file. To view the file, select <b>View XML</b> from the right-click menu.</p>
----------------------	---

## Remote Objects Property

User interface elements are described below:

UI Element	Description
<b>Record in-process objects</b>	Records activity between the client and server when the server is hosted in the same process as the client. Since the actions are not true client/server traffic, it is usually not of interest. When in-process methods are relevant, for example, in certain Enterprise Service applications, you can enable this option to capture them. <b>Default value:</b> disabled.
<b>Asynchronous calls</b>	Specifies how VuGen should handle asynchronous calls on remote objects and their callback methods <ul style="list-style-type: none"><li>• <b>Call original callbacks by default.</b> Uses the recorded application's original callback when generating and replaying the script. If the callback method is explicitly excluded by a filter, the callback will be excluded even if you enable this option.</li><li>• <b>Generate asynchronous callbacks.</b> This option defines how VuGen will handle callbacks when the original callbacks are not recorded.</li></ul> For more information, see " <a href="#">Asynchronous Calls</a> " on page 724.

<b>WCF duplex binding</b>	<ul style="list-style-type: none"><li>• <b>Generate dummy callback handler.</b> Replaces the original callback in duplex communication with a dummy callback, performing the following actions:<ul style="list-style-type: none"><li>▪ <b>Store arguments.</b> When the server calls the handler during replay, it saves the method arguments to a key-value in memory map.</li><li>▪ <b>Synchronize replay.</b> It stops the script execution until the next response arrives. VuGen places the synchronization at the point that the callback occurred during recording. This is represented in the script by a warning:</li></ul></li><li>• <b>Generate unique client base address.</b> If your application employs dual HTTP Binding, since HTTP is inherently not a duplex protocol, the framework uses a standard port to receive response data being passed to the callback. When you attempt to run multiple instances of your application, you may be unable to do so using the same port number. This option replaces the original client base address's port number with a unique port.</li></ul> <p>For background information about WCF duplex binding, see "<a href="#">Recording WCF Duplex Communication</a>" on page 720.</p>
---------------------------	--

## .NET > Shared DLLs

This dialog box enables you to specify the list of shared DLLs before you record a Vuser script. If a DLL is included in the list of shared DLLs, when the Vuser script is run and requires a particular DLL, the Vuser will access the DLL in its shared location – the DLL will not be copied to the load generator. Adding a DLL to the list of shared DLLs therefore saves hard-drive space on the load generator when a Vuser is run.

**Note:** The location that you specify for a shared DLL must be accessible to all load generators on which the Vuser will run.

After you record a Vuser script, the list of shared DLLs is copied from the Recording Options to the Run-Time Settings. For details on how to view and modify the run-time settings, see "[.NET > Shared DLLs](#)" on page 370.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Microsoft .NET &gt; Shared DLLs</b>
<b>See also</b>	<a href="#">".NET &gt; Shared DLLs"</a> on page 370

User interface elements are described below:

UI Element	Description

<b>DLL Entries</b>	The list of shared DLLs that VuGen will access while the Vuser script is being recorded. The order in which the DLLs appear in the list is significant. When a specific DLL is required, VuGen will access the first instance of that DLL in the list. If a specific DLL is not currently available, clear the check box to the left of the DLL entry. The DLL will remain in the list of shared DLLs. To enable the DLL, select the check box to the left of the DLL entry.
	<b>Down Arrow.</b> Moves the selected DLL entry down the list.
	<b>Up Arrow.</b> Moves the selected DLL entry up the list.
	<b>Add DLL.</b> Enables you to add a DLL to the list of shared DLLs.
	<b>Add DLL Folder.</b> This option is always disabled.
	<b>Delete.</b> Removes the selected DLL from the list of shared DLLs.

## Mobile TruClient Properties > Mobile Device Node

This pane enables you to select a mobile device properties when recording a TruClient Ajax - Mobile script.

<b>To access</b>	<ul style="list-style-type: none"> <li>VuGen &gt; Recording Options &gt; TruClient Ajax - MobileProperties &gt; Mobile Device</li> <li>Select <b>Mobile Device</b> button from the Main VuGen Toolbar</li> </ul> 
<b>Relevant tasks</b>	<a href="#">"How to Add, Remove, and Import Mobile Device Settings for Mobile TruClient" on page 716</a> <a href="#">"How to Record a Script with Mobile TruClient" on page 715</a>

User interface elements are described below:

UI Element	Description
<b>Mobile Device</b>	Select the mobile device type you want to test.

UI Element	Description
User Agent	Specify the header string that is sent to server to identify your mobile device. Once you have selected a device, the default header value will appear. However, this header string can be modified.
Display	Specify the height and width of your mobile device screen. Mobile TruClient will open browser window according to the display settings.

## Network > Port Mapping Node

Enables you to set the port mapping recording options.

To access	VuGen > Record > Recording Options > Network > Port Mapping
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
New Entry	Opens the Server Entry dialog box, allowing you to add a new mapping. For user interface details, see " <a href="#">Server Entry Dialog Box</a> " on the next page.
Edit Entry	Opens the Server Entry dialog box, allowing you to edit the selected entry. For user interface details, see " <a href="#">Server Entry Dialog Box</a> " on the next page.
Options...	Opens the Advanced Settings dialog box to enable auto-detection of the communication protocol and SSL level. For user interface details, see " <a href="#">Advanced Port Mapping Settings Dialog Box</a> " on page 229.
<Port Mapping list>	A list of the port mappings. You can temporarily disable any entry by clearing the check box adjacent to it. When you disable an entry, VuGen ignores all traffic to that server:port combination. You should disable the port entry when the data is irrelevant or if the protocol is not supported.

<b>Capture level</b>	The level of data to capture (relevant only for HTTP based protocols): <ul style="list-style-type: none"> <li><b>Socket level data.</b> Capture data using trapping on the socket level only. Port mappings apply in this case (default).</li> <li><b>WinINet level data.</b> Capture data using hooks on the <b>WinINet.dll</b> API used by certain HTTP applications. The most common application that uses these hooks is Internet Explorer. Port mappings are not relevant for this level.</li> <li><b>Socket level and WinINet level data.</b> Captures data using both mechanisms. WinINet level sends information for applications that use <b>WinINet.dll</b>. Socket level sends data only if it determines that it did not originate from <b>WinINet.dll</b>. Port mapping applies to data that did not originate from <b>WinINet.dll</b>.</li> </ul>
<b>Network-level server address mappings for</b>	Specifies the mappings per protocol. For example, to show only the FTP mappings, select FTP.

## Server Entry Dialog Box

Enables you to define a server from the server list in the network port mapping node.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Network &gt; Port Mapping &gt; New Entry / Edit Entry</b>
<b>Important information</b>	This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page <a href="#">246</a> .

User interface elements are described below:

Section	UI Element	Description
<b>Socket Service</b>	<b>Target Server</b>	The IP address or host name of the target server for which this entry applies. <b>Default value:</b> All Servers.
	<b>Service ID</b>	A protocol or service name used by the recorder to identify the type of connection (i.e. HTTP, FTP, and so on). You can also specify a new name. The name may not exceed 8 characters.
	<b>Record Type</b>	The type of recording—directly or through a proxy server.

	<b>Port</b>	<p>The port of the target server for which this entry applies. Entering <b>0</b> specifies all ports.</p> <p>If you do not specify all of the port and server names, VuGen uses the following priorities in assigning data to a service:</p> <ul style="list-style-type: none"> <li>• Priority 1: port and server specified</li> <li>• Priority 2: port not specified, server specified</li> <li>• Priority 3: port specified, server not specified</li> <li>• Priority 4: port and server not specified</li> </ul> <p>A map entry with a high priority does not get overridden by an entry with a lower priority. For example, if you specify that traffic on server twilight using port 25 be handled as SMTP and then you specify that all servers on port 25 be handled as HTTP, the data will be treated as SMTP.</p> <ul style="list-style-type: none"> <li>• <b>Forced mapping.</b> If you specify a mapping for a port number, server name, or combination server:port, VuGen forces the network traffic to use that service. For example, if you were to specify &lt;Any&gt; server on port 80 to use FTP, VuGen uses the FTP protocol to record that communication, even though the actual communication may be HTTP. In this instance, the Vuser script might be empty.</li> </ul>
	<b>Service Type</b>	The type of service, currently set to TCP.
	<b>Connection Type</b>	The security level of the connection: <b>Plain</b> (non-secure), <b>SSL</b> , or <b>Auto</b> . If you select Auto, the recorder checks the first 4 bytes for an SSL signature. If it detects the SSL signature, it assumes that SSL is being used.
<b>SSL Configuration</b>	<b>SSL Version</b>	<p>The preferred SSL version to use when communicating with the client application and the server.</p> <p><b>Default value:</b> SSL 2/3. However some services require SSL 3.0 only or SSL 2.0 only. Some new wireless applications require a the Transport Layer Security algorithm, TLS 1.x.</p>
	<b>SSL Cipher</b>	The preferred SSL cipher to use when connecting with a remote secure server.
	<b>Use specified client-side certificate</b>	The default client-side certificate to use when connecting to a remote server. Specify or browse for a certificate file in <b>txt</b> , <b>crt</b> , or <b>pem</b> format, and supply a password.

	<b>Use specified proxy-server certificate</b>	The default server certificate to present to client applications that request a server certificate. Specify or browse for a certificate file in <b>txt</b> , <b>crt</b> , or <b>pem</b> format, and supply a password. Click <b>Test SSL</b> to check the authentication information against the server.
--	---	--

## Advanced Port Mapping Settings Dialog Box

Enables you to set the advanced port mapping settings. For more information, see "[Port Mapping Auto Detection](#)" on page 250.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Network &gt; Port Mapping &gt; Options</b>
<b>Important information</b>	This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Enable auto SSL detection</b>	Automatically detects SSL communication. Specify the version and default cipher that you want to detect. Note that this only applies to port mappings that were defined as <b>auto</b> in the <b>Connection type</b> box, or not defined at all. If a server, port, or server:port combination was defined as either <b>Plain</b> or <b>SSL</b> , then auto SSL detection does not apply.
<b>Enable auto detection of SOCKET based communication</b>	Automatically detects the type of communication. If required, raise the maximum number of transitions, one at a time until VuGen succeeds in detecting the protocol. You can also gradually increase the maximum buffer size by 1024 bytes (1 KB) at a time until VuGen succeeds in detecting the protocol. This allows VuGen to review a larger amount of data in order to find a signature.
<b>Log Level</b>	Sets the logging level for the automatic socket detection.

## RDP > Code Generation > Advanced Node

Enables you to control the way VuGen creates an RDP script. Only advanced users are advised to modify these settings.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; RDP &gt; Code Generation - Adv</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Correlate clipboard parameters</b>	Replaces the recorded clipboard text sent by the user with the correlated parameter containing the same text as received from the server.
<b>Double-click timeout (msec)</b>	The maximum time (in milliseconds) between two consecutive mouse button clicks to be considered a double-click. <b>Default value:</b> 500 milliseconds.
<b>Prefix for clipboard parameters</b>	The prefix for clipboard parameters generated in the current script. This is useful when merging scripts, allowing you to specify a different prefix for each script. <b>Default value:</b> ClipboardDataParam_.
<b>Prefix for snapshot names</b>	The prefix for snapshot file names generated in the current script. This is useful when merging scripts—you can specify a different prefix for each script. <b>Default value:</b> snapshot_.

## RDP > Code Generation > Agent Node

Enables you to control the way the agent for Microsoft Agent for Terminal Server functions with VuGen during recording.

<b>To access</b>	VuGen > Record > Recording Options > RDP > Code Generation - Agent
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Use RDP agent</b>	Generates script using extended information gathered by the RDP agent. The LoadRunner RDP agent must be installed on the server. For details, see " <a href="#">How to Install / Uninstall the RDP Agent</a> " on page 755.  <b>Note:</b> To utilize this feature, you must enable the <b>Replay with RDP agent</b> Run Time settings. For details, see " <a href="#">RDP &gt; RDP Agent Node</a> " on page 374

<b>Enable RDP agent log</b>	<p>Enables the RDP agent log.</p> <ul style="list-style-type: none"><li><b>RDP agent log detail level.</b> Configures the level of detail generated in the RDP agent log with <b>Standard</b> being the lowest level of detail and <b>Extended Debug</b> being the highest level of detail.</li><li><b>RDP agent log destination.</b> Configures the destination of the RDP agent log data. <b>File</b> saves the log messages only on the remote server side. <b>Stream</b> sends the log messages to the VuGen machine. <b>FileAndStream</b> sends the log messages to both destinations.</li><li><b>RDP agent log folder.</b> The folder path on the remote server that the RDP agent log file will be generated in.</li></ul>
-----------------------------	---

## **RDP > Code Generation > Basic Node**

Enables you to control the way VuGen creates a script—the level of detail, triggers, and timeouts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; RDP &gt; Code Generation - Basic</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Always generate connection name</b>	If selected, function call will contain the <b>ConnectionName</b> parameter. If not selected, the functions will only contain this parameter if more than a single <b>rdp_connect_server</b> appears in the script. <b>Default value:</b> disabled.
<b>Automatic generation of synchronization points</b>	Synchronization points allow the script to pause in the replay while waiting for a window or dialog to pop-up, or some other control to fulfil a certain condition. This option automatically generates <b>sync_on_image</b> functions before mouse clicks and drags (enabled by default). The <b>Sync radius</b> is the distance from the mouse operation to the sides of the rectangle which defines the synchronization area. The default is 20 pixels. Select one of the following options: <ul style="list-style-type: none"><li><b>None.</b> No synchronization points are automatically added.</li><li><b>Rectangular.</b> Creates synchronization points as rectangular boxes centered around the click or drag location.</li><li><b>Enhanced.</b> Creates synchronization points designed to select only the desired location (e.g. a button) and to react to changes in the UI (e.g. the button moves). If a synchronization region is not recognized, the rectangular synchronization settings are used.</li></ul>

UI Element	Description
<b>Generate mouse movement calls</b>	Generates <b>rdp_mouse_move</b> calls in the script. When enabled, this option significantly increases the script size. <b>Default value:</b> disabled.
<b>Generate raw keyboard calls</b>	Generates <b>rdp_raw_key_up/down</b> calls as if the script level was set to <b>Raw</b> . Mouse calls will still be generated according to the script level. If disabled, VuGen generates Keyboard calls according to the script level. If the script level is set to <b>Raw</b> , this option is ignored. <b>Default value:</b> disabled.
<b>Generate raw mouse calls</b>	Generates <b>rdp_mouse_button_up/down</b> calls as if the script level was set to Raw. Keyboard calls will still be generated according to the script level. If disabled, VuGen generates Mouse calls according to the script level. If the script level is set to <b>Raw</b> , this option is ignored. <b>Default value:</b> disabled.
<b>Script generation level</b>	The level of the script and the type of API functions to use when generating the script. <ul style="list-style-type: none"> <li><b>High.</b> Generate high level scripts. Keyboard events are translated to <b>rdp_type</b> calls. Two consecutive mouse clicks with the same coordinates are translated as a double-click.</li> <li><b>Low.</b> Generate low level scripts. Key up/down events are translated into <b>rdp_key</b> events. Modifier keys (Alt, Ctrl, Shift) are used as a <b>KeyModifier</b> parameter for other functions. Mouse up/down/ move events are translated to mouse click/drag events.</li> <li><b>Raw.</b> Generates a script on a raw level, by extracting input events from network buffers and generating calls in their simplest form: key up/down, mouse up/down/move. The <b>KeyModifier</b> parameter is not used.</li> </ul>

## RDP > Client Startup Node

Enables you to set the RDP client startup recording options.

To access	VuGen > Record > Recording Options > RDP > Client Startup
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Run RDP client application</b>	Connects to the terminal server by running the Terminal Services client.
<b>Use custom connection file</b>	Connects to the terminal server by using an existing connection file. The file should have an <b>*.rdp</b> extension. You can browse for the file on your file system or network.
<b>Use default connection file</b>	Connects to the terminal server by using the <b>Default.rdp</b> file in your document's folder.

## Recording Properties > Corba Options Node

Enables you to set the CORBA specific recording properties and several callback options.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Recording Properties &gt; Corba Options</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Record CallBack Connection</b>	Instructs VuGen to generate a connect statement for the connection to the ORB, for each callback object. <b>Default value:</b> disabled.
<b>Record DLL only</b>	Instructs VuGen to record only on a DLL level. <b>Default value:</b> disabled.
<b>Record Properties</b>	Instructs VuGen to record system and custom properties related to the protocol. <b>Default value:</b> enabled.
<b>Resolve CORBA Objects</b>	When correlation fails to resolve a CORBA object, recreate it using its binary data. <b>Default value:</b> disabled.
<b>Show IDL Constructs</b>	Displays the IDL construct that is used when passed as a parameter to a CORBA invocation. <b>Default value:</b> enabled.
<b>Use local vendor classes</b>	Use local vendor classes and add the <b>srv</b> folder to the BOOT classpath. If you disable this option, VuGen uses network classes and adds the script's classes to the classpath. <b>Default value:</b> enabled.
<b>Vendor</b>	The CORBA vendors: <b>Inprise Visibroker</b> , <b>Iona OrbixWeb</b> , or <b>Bea Weblogic</b> .

## Recording Properties > Correlation Options Node

Allows you to enable automatic correlation, and control its depth.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Recording Properties &gt; Correlation Options</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Advanced Correlation</b>	Enables correlation on complex objects such as arrays and CORBA container constructs and arrays. This type of correlation is also known as deep correlation. <b>Default value:</b> enabled.
<b>Correlate Collection Type</b>	Correlates objects from the Collection class for JDK 1.2 and higher. <b>Default value:</b> disabled.
<b>Correlate String Arrays</b>	Correlate strings within string arrays during recording. If disabled, strings within arrays are not correlated and the actual values are placed in the script. <b>Default value:</b> enabled.
<b>Correlate Strings</b>	Correlate strings in script during recording. If disabled, the actual recorded values are included in the script between quotation marks and all other correlation options are ignored <b>Default value:</b> disabled.
<b>Correlation Level</b>	Indicates the level of deep correlation, the number of inner containers to be scanned. <b>Default value:</b> 15.

## Recording Properties > Log Options Node

Enables you to determine the level of debug information generated during recording.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Recording Properties &gt; Log Options</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Class Dumping</b>	Dumps all of the loaded classes to the script folder. <b>Default value:</b> disabled.
<b>Digest Calculation</b>	Generate a digest of all recorded objects. <b>Default value:</b> disabled. <ul style="list-style-type: none"> <li>• <b>Exclude from Digest.</b> A list of objects not to be included in the digest calculation.</li> </ul> <b>Syntax:</b> java.lang.Object class format, delimiter = ","
<b>Log Level</b>	The level of recording log to generate: <ul style="list-style-type: none"> <li>• <b>None.</b> No log file is created</li> <li>• <b>Brief.</b> Generates a standard recording log and output redirection</li> <li>• <b>Detailed.</b> Generates a detailed log for methods, arguments, and return values.</li> <li>• <b>Debug.</b> Records hooking and recording debug information, along with all of the above.</li> </ul>
<b>Synchronize Threads</b>	For multi-threaded applications, instructs VuGen to synchronize between the different threads. <b>Default value:</b> disabled.

## Recording Properties > Recorder Options Node

Enables you to set the Java protocol to record as well as other protocol specific recording options.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Recording Properties &gt; Recorder Options</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Byte Array Format</b>	The format of byte arrays in a script: Regular, Unfolded Serialized Objects, or Folded Serialized Objects. Use one of the serialized object options when recording very long byte arrays. <b>Default value:</b> Regular.
<b>Bytes as Characters</b>	Displays readable characters as characters with the necessary casting—not in byte or hexadecimal form. <b>Default value:</b> enabled.

UI Element	Description
<b>Comment Lines Containing</b>	Comment out all lines in the script containing one of the specified strings. To specify multiple strings, separate the entries with commas. <b>Default value:</b> Any line with a string containing <undefined> will be commented out.
<b>Extensions List</b>	A comma separated list of all supported extensions. Each extension has its own hooks file. <b>Default value:</b> JNDI.
<b>Insert Functional Check</b>	Inserts verification code that compares the return value received during replay, to the expected return value generated during recording. This option only applies to primitive return values. <b>Default value:</b> disabled.
<b>Load Parent Class Before Class</b>	Change the loading order so that parent classes are loaded before child classes. This helps identify hooking for trees with deep inheritance. <b>Default value:</b> enabled.
<b>Record LoadRunner Callback</b>	Records the LoadRunner stub object as a callback. If disabled, VuGen records the original class as the callback. <b>Default value:</b> enabled.
<b>Recorded Protocol</b>	Specifies which protocol to record: RMI, CORBA, JMS, or Jacada. <b>Default value:</b> RMI.
<b>Remove Lines Containing</b>	Remove all lines containing one of the specified strings from the script. To specify multiple strings, separate the entries with commas. This feature is useful for customizing the script for a specific testing goal.
<b>Unreadable Strings as Bytes</b>	Represents strings containing unreadable characters as byte arrays. This option applies to strings that are passed as parameters to invocations. <b>Default value:</b> enabled.
<b>Use _JAVA_OPTIONS flag</b>	Forces JVM versions 1.2 and higher to use the _JAVA_OPTION environment variable which contains the desired JVM parameters. <b>Default value:</b> disabled.
<b>Use DLL hooking to attach LoadRunner support</b>	Use DLL hooking to automatically attach LoadRunner support to any JVM.

## **Recording Properties > Serialization Options Node**

Enables you to control how objects are serialized. Serialization is often relevant to displaying objects in an ASCII representation in order to parameterize their values.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Recording Properties &gt; Serialization Options</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, <a href="#">"Protocol Compatibility Table" on page 246</a> .
<b>See also</b>	<a href="#">"How to Correlate Scripts - Java Scripts - Serialization" on page 296</a>

User interface elements are described below:

UI Element	Description
<b>Unfold Serialized Objects</b>	<p>Expands serialized objects in ASCII representation and allows you to view the ASCII values of the objects in order to perform parameterization.</p> <ul style="list-style-type: none"> <li>• <b>Limit Object Size (bytes).</b> Limits serializable objects to the specified value. Objects whose size exceeds this value, will not be given ASCII representation in the script.</li> </ul> <p><b>Default value:</b> 3072 bytes.</p> <ul style="list-style-type: none"> <li>• <b>Ignore Serialized Objects.</b> Lists the serialized objects not to be unfolded when encountered in the recorded script. Separate objects with commas.</li> </ul> <p><b>Syntax:</b> java.lang.Object class format, delimiter = ","</p> <ul style="list-style-type: none"> <li>• <b>Serialization Delimiter.</b> Indicates the delimiter separating the elements in the ASCII representation of objects. VuGen will only parameterize strings contained within these delimiters. The default delimiter is '#'.</li> </ul> <ul style="list-style-type: none"> <li>• <b>Unfold Arrays.</b> Expands array elements of serialized objects in ASCII representation. If you disable this option and an object contains an array, the object will not be expanded.</li> </ul> <p><b>Default value:</b> enabled—all deserialized objects are totally unfolded.</p> <ul style="list-style-type: none"> <li>▪ <b>Limit Array Entries.</b> Instructs the recorder not to open arrays with more than the specified number of elements. <b>Default value:</b> 200.</li> </ul>

## RTE > Configuration Node

Enables you to set the recording options to match the character set used during terminal emulation.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; RTE &gt; Configuration</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see <a href="#">"Protocol Compatibility Table" on page 246</a> .

User interface elements are described below:

UI Element	Description
Character Set	Match the character set used during terminal emulation. The default character set is ANSI. For Kanji and other multi-byte platforms, you can specify DBCS (Double-byte Character Set).

## RTE > RTE Node

Enables you to set the general RTE recording options.

To access	VuGen > Record > Recording Options > RTE > RTE
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
Generate automatic synchronization commands	<p>Automatically generates a number of <b>TE-synchronization</b> functions, and insert them into the script while you record.</p> <ul style="list-style-type: none"><li><b>Cursor.</b> Generate a <b>TE_wait_cursor</b> function before each <b>TE_type</b> function.</li><li><b>Prompt.</b> Generate a <b>TE_wait_text</b> function before each <b>TE_type</b> function (where appropriate).</li><li><b>X-System.</b> Generate a <b>TE_wait_sync</b> function each time a new screen is displayed while recording.</li></ul> <p><b>Note:</b> VuGen generates meaningful <b>TE_wait_text</b> functions when recording VT type terminals only. Do not use automatic <b>TE_wait_text</b> function generation when recording block-mode (IBM) terminals.</p>
Generate automatic X-System transaction	Records the time that the system was in the X SYSTEM mode during a scenario run. This is accomplished by inserting a <b>TE_wait_sync_transaction</b> function after each <b>TE_wait_sync</b> function. Each <b>TE_wait_sync_transaction</b> function creates a transaction with the name <b>default</b> . Each <b>TE_wait_sync_transaction</b> function records the time that the system spent in the previous X SYSTEM state.

<b>Generate screen header comments</b>	Generates screen header comments while recording a Vuser script, and inserts the comments into the script. A generated comment contains the text that appears on the first line of the terminal emulator window.  <b>Note:</b> You can generate comments automatically only when using block-mode terminal emulators such as the IBM 5250.
<b>Keyboard record timeout</b>	When you type text into a terminal emulator while recording, VuGen monitors the text input. After each keystroke, VuGen waits up to a specified amount of time for the next key stroke. If there is no subsequent keystroke within the specified time, VuGen assumes that the command is complete.

## SAPGUI > Auto Logon Node

Enables you to log on automatically when you begin recording. The logon functions are placed in the vuser\_init section of the script.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; SAPGUI &gt; Auto Logon</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Enable Auto logon</b>	Enables you to log on automatically when you begin recording. Enter the <b>Server name</b> , <b>User</b> , <b>Password</b> , <b>Client name</b> , and interface <b>Languages</b> for the SAP server.

## SAPGUI > Code Generation Node

Enables you to set the code generation settings for the SAPGUI protocol.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; SAPGUI &gt; Code Generation</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description

<b>Always generate Object ID in header file</b>	Places the Object IDs in a separate header file instead of in the script. When you disable this option, VuGen generates the IDs according to the specified string length in the general script setting. This results in a more compact and cleaner script.
<b>Generate Fill Data steps</b>	Generates Fill Data steps for table and grid controls—instead of separate steps for each cell.
<b>Generate logon operation as a single step</b>	Generates a single <b>sapgui_logon</b> method for all of the logon operations. This helps simplify the code. If you encounter login problems, disable this option.

## SAPGUI > General Node

Enables you to set the general recording options for the SAPGUI protocol.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; SAPGUI &gt; General</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.

User interface elements are described below:

UI Element	Description
<b>Capture screen snapshots</b>	Indicates how to save the snapshots of the SAPGUI screens as they appear during recording: <b>ActiveScreensnapshots</b> , <b>Regular snapshots</b> , or <b>None</b> . ActiveScreen snapshots provide more interactivity and screen information after recording, but they require more resources.
<b>Changing events during recording</b>	<b>Process Context menus by text.</b> Processes context menus by their text, generating <b>sapgui_toolbar_select_context_menu_item_by_text</b> functions. When disabled, VuGen processes context menus by their IDs, and generates a <b>sapgui_toolbar_select_context_menu_item</b> for context menus. This is an advantage when working with Japanese characters.

## Silverlight > Services Node

Enables you to manage WSDL files in Silverlight Protocol scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Silverlight &gt; Services</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>Relevant tasks</b>	<a href="#">"How to Import WSDL Files" on page 801</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Service list>	The list of imported WSDL files and their locations. The toolbar allows you to add, delete and edit WSDL files. Additionally, select the Protocol and Security Data button to edit Protocol and Security Data.
<b>Automatically detect WSDL files and import services during code generation</b>	Automatically attempts to locate and import WSDL files used in your script.
<b>Do not use WSDL files</b>	Disables WSDL files in your script, generating SOAP requests instead. This results in a lower level script, however it generally increases the script performance.
<b>Service Endpoint</b>	The location of the endpoint at which a given WSDL is available.
<b>Use WSDL files included in the script</b>	Enables WSDL files imported automatically or manually.
<b>WSDL Location</b>	The location of the selected WSDL file.

## Add / Edit Services Dialog Box

Enables you to locate and import WSDLs to a Silverlight Protocol script.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Silverlight &gt; Services &gt; Add</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>Relevant tasks</b>	<a href="#">"How to Import WSDL Files" on page 801</a>

User interface elements are described below:

UI Element	Description
Connection Settings	Opens the Connection Settings dialog box, enabling you to configure the proxy and authentication information for the specified WSDL file. For user interface information, see " <a href="#">Connection Settings Dialog Box</a> " on the next page.

<b>Select WSDL from</b>	<ul style="list-style-type: none"><li><b>URL.</b> Select the WSDL by specifying the URL.</li><li><b>File.</b> Select the WSDL by specifying the local path.</li><li><b>Previously Imported.</b> Select the WSDL from the WSDL History (list of previously imported WSDL files).</li></ul>
<b>Service Endpoint</b>	The location of the endpoint at which a given WSDL is available.
<b>WSDL Location</b>	The URL or local path to the WSDL.

## Connection Settings Dialog Box

Configures the proxy and authentication information for WSDL files in Silverlight Protocol scripts.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Silverlight &gt; Services &gt; Add &gt; Connection Settings</b>
<b>Important information</b>	<ul style="list-style-type: none"><li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 246</a>.</li><li>These settings are only relevant for importing WSDL files. To configure authentication and proxy information for WSDL files to be used during replay, add a <code>web_set_user_step</code> function with the desired values.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Import WSDL Files" on page 801</a>

User interface elements are described below:

UI Element	Description
<b>Authentication</b>	Enable the authentication settings by selecting <b>Use Authentication Settings</b> and entering your user name and password.
<b>Proxy</b>	Enable the proxy settings by selecting <b>Use Proxy Settings</b> and entering your user name, password, server, and port number.

## Protocol and Security Scenario Data Dialog Box

Enables you to configure the protocol and security scenario data settings.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Silverlight &gt; Services &gt; Protocol and Security Data Button</b>
------------------	---

<b>Important information</b>	<ul style="list-style-type: none"><li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on page 246.</li><li>These settings are only relevant for importing WSDL files. To configure authentication and proxy information for WSDL files to be used during replay, add a <b>web_set_user_step</b> function with the desired values.</li><li>The settings in this dialog box are reset during code generation.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Import WSDL Files" on page 801</a>

User interface elements are described below:

UI Element	Description
<b>Port</b>	An individual endpoint for a WSDL binding.  <b>Note:</b> [REDACTED] [REDACTED]
<b>Transport</b>	The transport layer protocol used by VuGen to send service requests to the server. You can select HTTP, HTTPS, or LrHTTP.  <b>Note:</b> HTTP is not compatible with UserNameOverTransport security and HTTPS requires that you select UserNameOverTransport security.
<b>Encoding</b>	The encoding method to be used for service requests sent to the server.
<b>WS Addressing version</b>	The WS-Addressing version for the selected WSDL file.
<b>Security</b>	
<b>Authentication mode</b>	Enable authentication by selecting <b>UserNameOverTransport</b> mode. <b>Default mode:</b> None.
<b>Username</b>	When authentication is enabled, a valid username is required.
<b>Password</b>	When authentication is enabled, a valid password is required.

## Traffic Analysis > Traffic Filter

This dialog box enables you to filter either incoming or outgoing traffic.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; Traffic Analysis &gt; Traffic Filters</b>
<b>Important information</b>	<ul style="list-style-type: none"> <li>For details, see "<a href="#">Analyzing Traffic</a>" on page 698.</li> <li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see the "<a href="#">Protocol Compatibility Table</a>" on page 246.</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Create a Script by Analyzing Traffic" on page 704</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>When generating the script</b>	<b>Include all IP addressing the list.</b> check box to include traffic from specified IP address. <b>Exclude all IP address in the list.</b> check box to exclude traffic from specified IP addresses.
<b>&lt;Incoming Traffic Tab&gt;</b>	
Enables you to identify IP addresses for incoming traffic	
	Add an IP address
<b>Source IP</b>	Specify the IP address of the server.
	Delete IP address
<b>&lt;Outgoing Traffic Tab&gt;</b>	
Enables you to identify IP addresses for outgoing traffic	
	Add an IP address
<b>Destination IP</b>	Specify the IP address of the server.
<b>Destination Port</b>	Specify the destination port of the server.
	Delete IP address

## WinSock Node

Enables you to set the WinSock recording options.

<b>To access</b>	<b>VuGen &gt; Record &gt; Recording Options &gt; WinSock</b>
------------------	--

<b>Important information</b>	When using translation tables on Solaris machines, you must set the following environment variables on all machines running scripts: <code>setenv LRSDRV_SERVER_FORMAT 0025</code> <code>setenv LRSDRV_CLIENT_FORMAT 04e4</code>
<b>Relevant tasks</b>	<a href="#">"How to Record a Windows Sockets Script" on page 959</a>

User interface elements are described below:

UI Element	Description
	Adds a new entry to the list of excluded sockets.
	Removes the selected entry from the list of excluded sockets.
<b>Do not include excluded socket in log</b>	Excludes the sockets on the list from the log. Clearing this option enables logging for the excluded sockets. Their actions are preceded by "Exclude" in the log file.
<b>Exclude Settings/Socket List</b>	The host and port of the sockets to exclude from the recording or regeneration of the script. Use the following syntax: <ul style="list-style-type: none"> <li>• <b>host:port</b> format excludes a specific port.</li> <li>• <b>host</b> format excludes all ports for the specified host.</li> <li>• <b>:port</b> format excludes a specific port on the local host.</li> <li>• <b>*:port</b> format excludes a specific port on all hosts.</li> </ul>
<b>Encoding Method</b>	<b>Use OEM encoding.</b> Enable data encoding that supports non-English characters. <b>Use ASCII encoding.</b> Enable data encoding that is limited to English characters. Use this option to replicate the LR 9.5x data encoding method.
<b>Think Time Threshold</b>	During recording, VuGen automatically inserts the think time steps when you pause between actions. You can set a threshold level, below which the recorded think time will be ignored. <b>Default value:</b> five seconds.

<b>Translation tables</b>	<p>The Translation Table lets you specify the format for recording sessions when using the WinSock single protocol, and for code generation when using a WinSock multi protocol. This applies to users running on mainframe machines or AS/400 servers. Both the server and client machines determine the format of the data from translation tables installed on your system. Select a translation option from the list box.</p> <p>The first four digits of the listbox item represent the server format. The last four digits represent the client format.</p> <p>The translation tables are located in the <b>ebcdic</b> folder under the VuGen's installation folder. If your system uses different translation tables, copy them to the <b>ebcdic</b> folder.</p> <p><b>Note:</b> If your data is in ASCII format, it does not require translation. Select the <b>None</b> option, the default value.</p>
---------------------------	---

## ***Recording Options - Miscellaneous Topics***

This section contains a variety of topics relating to recording options.

### ***Protocol Compatibility Table***

The following table lists the Vuser protocols and which recording option nodes are available for each protocol.

Protocol	Recording Options Nodes
Ajax - Click & Script	<ul style="list-style-type: none"><li>General - Script, Recording</li><li>GUI Properties - Advanced, Web Event Configuration</li><li>Network - Port Mapping</li><li>HTTP Properties - Advanced, Correlation</li></ul>
Ajax TruClient	<ul style="list-style-type: none"><li>None</li></ul>
C Vuser	<ul style="list-style-type: none"><li>None</li></ul>
Citrix ICA	<ul style="list-style-type: none"><li>General - Script</li><li>Citrix - Configuration, Recorder, Code Generation, Login</li></ul>
COM/DCOM	<ul style="list-style-type: none"><li>General - Script</li><li>COM/DCOM - Filter, Options</li></ul>
DNS	<ul style="list-style-type: none"><li>None</li></ul>

Protocol	Recording Options Nodes
<b>FTP</b>	<ul style="list-style-type: none"> <li>• General - Script</li> <li>• Network - Port Mapping</li> </ul>
<b>Flex (AMF/RTMP)</b>	<ul style="list-style-type: none"> <li>• General - Script, Protocols, Recording</li> <li>• Flex - RTMP, Configuration, Externalizable Objects, AMF</li> <li>• Network - Port Mapping</li> <li>• HTTP Properties - Advanced, Correlation</li> </ul>
<b>IMAP</b>	<ul style="list-style-type: none"> <li>• General - Script</li> <li>• Network - Port Mapping</li> </ul>
<b>Java over HTTP</b>	<ul style="list-style-type: none"> <li>• General - Recording</li> <li>• Java Environment Settings - Java VM, Classpath</li> <li>• Network - Port Mapping</li> <li>• HTTP Properties - Browser, Recording Proxy, Advanced, Correlation</li> </ul>
<b>Java Record Replay</b>	<ul style="list-style-type: none"> <li>• Java Environment Settings - Java VM, Classpath</li> <li>• Recording Properties - Recorder Options, Serialization Options, Correlation Options, Log Options, Corba Options</li> </ul>
<b>Java Vuser</b>	<ul style="list-style-type: none"> <li>• None</li> </ul>
<b>LDAP</b>	<ul style="list-style-type: none"> <li>• General - Script</li> </ul>
<b>MMS (Media Player)</b>	<ul style="list-style-type: none"> <li>• None</li> </ul>
<b>Microsoft .NET</b>	<ul style="list-style-type: none"> <li>• General - Script</li> <li>• .NET - Recording, Filters</li> </ul>
<b>Microsoft Remote Desktop Protocol (RDP)</b>	<ul style="list-style-type: none"> <li>• General - Script</li> <li>• RDP - Client Startup, Code Generation (Basic, Advanced, and Agent)</li> <li>• Network - Port Mapping</li> </ul>
<b>MAPI (Microsoft Exchange)</b>	<ul style="list-style-type: none"> <li>• None</li> </ul>

Protocol	Recording Options Nodes
<b>MMS (Multimedia Messaging Service)</b>	<ul style="list-style-type: none"> <li>General - Script</li> </ul>
<b>ODBC</b>	<ul style="list-style-type: none"> <li>General - Script</li> <li>Database - Database</li> </ul>
<b>Oracle (2-Tier)</b>	<ul style="list-style-type: none"> <li>General - Script</li> <li>Database - Database</li> </ul>
<b>Oracle NCA</b>	<ul style="list-style-type: none"> <li>General - Script, Protocols, Recording</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> </ul>
<b>Oracle Web Applications 11i</b>	<ul style="list-style-type: none"> <li>General - Script, Recording</li> <li>GUI Properties - Advanced, Web Event Configuration</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> </ul>
<b>POP3</b>	<ul style="list-style-type: none"> <li>General - Script</li> <li>Network - Port Mapping</li> </ul>
<b>SAP Click &amp; Script</b>	<ul style="list-style-type: none"> <li>General - Script, Recording</li> <li>GUI Properties - Advanced, Web Event Configuration</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> </ul>
<b>SAP - Web</b>	<ul style="list-style-type: none"> <li>General - Script, Recording</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> </ul>
<b>SAP GUI</b>	<ul style="list-style-type: none"> <li>General - Script</li> <li>SAP GUI - General, Code Generation, Auto Logon</li> </ul>

Protocol	Recording Options Nodes
<b>Siebel - Web</b>	<ul style="list-style-type: none"> <li>General - Script, Protocols, Recording</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> </ul>
<b>Silverlight</b>	<ul style="list-style-type: none"> <li>General - Script, Protocols, Recording</li> <li>Silverlight - Services</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> <li>Data Format Extensions - Chain Configuration, Code Generation</li> </ul>
<b>SMTP</b>	<ul style="list-style-type: none"> <li>General - Script</li> <li>Network - Port Mapping</li> </ul>
<b>Web (HTTP/HTML)</b>	<ul style="list-style-type: none"> <li>General - Script, Protocols, Recording</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> <li>Data Format Extension - Chain Configuration, Code Generation</li> </ul>
<b>Web Services</b>	<ul style="list-style-type: none"> <li>General - Script, Protocols, Recording</li> <li>Traffic Analysis - Traffic Filters</li> <li>Network - Port Mapping</li> <li>HTTP Properties - Advanced, Correlation</li> </ul>
<b>Windows Sockets</b>	<ul style="list-style-type: none"> <li>Sockets - Winsock</li> </ul>

## Port Mapping Overview

When recording Vuser scripts that record network traffic on a socket level (HTTP, SMTP, POP3, FTP, IMAP, Oracle NCA and WinSock), you can set the Port Mapping options. Using these options, you can map the traffic from a specific server:port combination to the desired communication protocol.

The available communication protocols to which you can map are FTP, HTTP, IMAP, NCA, POP3, SMTP, and SOCKET. You create a mapping by specifying a server name, port number, or a complete server:port combination. For example, you can indicate that all traffic from the server *twilight* on port 25, should be handled as SMTP. You can also specify that all traffic from the server

called *viper*, should be mapped to the FTP protocol, regardless of the port. Additionally, you can map all traffic on port 23 to SMTP, regardless of the server name.

When recording in multi-protocol mode, If at least one of the protocols records on a socket level, the Port Mapping node will be available. The only exception is when you record HTTP or WinSock as a single protocol script.

## **Port Mapping Auto Detection**

VuGen's advanced port-mapping options let you configure the **auto-detection** options. VuGen's auto-detection analyzes the data that is sent to the server. It checks the data for a signature, a pattern in the data's content, that identifies the protocol. For the purpose of detecting a signature, all of the send buffers until the first receive buffer, are combined. All send buffers that were sent until a receive buffer is returned, are considered a single data **transition**. By default, no mappings are defined and VuGen employs auto-detection. In some protocols, VuGen determines the type in a single transition, (such as HTTP). Other network protocols require several transitions before determining the type. For this purpose, VuGen creates a temporary buffer for each server-port combination. If VuGen cannot determine the protocol type by reading the first transition buffers, it stores the data in a temporary buffer. It continues to read the incoming buffers until it detects a signature of a specific protocol.

By default, VuGen allows 4 transitions and uses a temporary buffer of 2048 bytes in order to detect a protocol signature. If VuGen has not yet determined the type after reaching the maximum number of transitions, or after reaching the maximum buffer size, it assigns the data to the WinSock protocol. If you did not instruct VuGen to record the WinSock protocol (in the multi-protocol selection), VuGen discards the data.

You can change the maximum number of buffers you want VuGen to read in order to detect the protocol type. You can also specify the size of the temporary buffer. In instances where the amount of data in the first send buffers, is greater than the size of the temporary buffer, VuGen cannot auto-detect the protocol type. In this case, you should increase the size of the temporary buffer.

When working with the above network level protocols, we recommend that you allow VuGen to use auto-detection to determine the protocol type. In most cases, VuGen's recorder is able to recognize the signatures of these protocols. It then automatically processes them according to the protocol specifications. In certain instances, however, VuGen may be unable to recognize the protocol. For example:

- The protocol signature closely resembles an existing protocol, resulting in erroneous processing.
- There is no unique signature for the protocol.
- The protocol uses SSL encryption, and therefore cannot be recognized on a WinSock level.

In all of the above cases, you can supply information to uniquely identify the server and port hosting the protocol.

## EUC-Encoding (Japanese Windows only)

When working with non-Windows standard character sets, you may need to perform a code conversion. A character set is a mapping from a set of characters to a set of integers. This mapping forms a unique character-integer combination for a given alphabet. Extended UNIX Code (EUC) and Shift Japan Industry Standard (SJIS) are non-Windows standard character sets used to display Japanese characters on Web sites.

Windows uses SJIS encoding, while UNIX uses EUC encoding. When a Web server is running UNIX and the client is running Windows, the characters in a Web site are not displayed on the client machine properly due to the difference in the encoding methods. This affects the display of EUC-encoded Japanese characters in a Vuser script.

During recording, VuGen detects the encoding of a Web page through its HTTP header. If the information on the character set is not present in the HTTP header, it checks the HTML meta tag.

If you know in advance that a Web page is encoded in EUC, you can instruct VuGen to use the correct encoding by using the recording options. To record a page in EUC-encoding, enable the **EUC** option in the Recording Options **Recording** node (only visible for Japanese Windows).

Enabling the **EUC** option forces VuGen to record a Web page in EUC encoding, even when it is not EUC-encoded. Therefore, you should only enable this option when VuGen cannot detect the encoding from the HTTP header or the HTML meta tag or when you know in advance that the page is EUC-encoded.

During recording, VuGen receives an EUC-encoded string from the Web server and converts it to SJIS. The SJIS string is saved in the script's **Action** function. However, for replay to succeed, the string has to be converted back to EUC before being sent back to the Web server. Therefore, VuGen adds a **web\_sjis\_to\_euc\_param** function before the **Action** function, which converts the SJIS string back to EUC.

In the following example, the user navigates to an EUC-encoded Web page and clicks a link. VuGen records the **Action** function and adds the **web\_sjis\_to\_euc\_param** function to the script before the **Action** function.

```
web_sjis_to_euc_param("param_link","Search");
web_link("LinkStep","Text={param_link}");
```

For more information, see "[Advanced URL Dialog Box](#)" on page 201.

## Script Generation Preference Overview

Before you record a session, VuGen allows you to specify a language for script generation. The available languages for script generation vary per protocol. The most common available languages are C and Java. By default, VuGen generates a script in the most common language for that protocol, but you can change this through the **Script** recording options node.

For user interface details, see "[General > Script Node](#)" on page 203.

**Tip:** If you record a script in one language, you can regenerate it in another language after the

recording. For task details, see ["How to Regenerate a Vuser Script" on page 266](#).

After you select a generation language, you can enable language-specific recording options which instruct the recorder what to include in the script and how to generate it.

If at least one of the protocols you are recording has multi-protocol capabilities, the Script node will be available except when you record HTTP or WinSock as a single protocol script.

## **Script Language Options**

When you record a session, VuGen creates a script that emulates your actions. The default script generation language is C. The following list specifies which protocols are appropriate for each language:

- **C.** For recording applications that use complex COM constructs and C++ objects.
- **C #.** For recording applications that use complex applications and environments (MS .NET protocol only).
- **Visual Basic .NET.** For VB .NET applications using the full capabilities of VB.

After the recording session, you can modify the script with regular C, C#, or VB .NET code and control flow statements.

## **Recording Levels - Overview**

VuGen lets you specify what information to record and which functions to use when generating a Vuser script by selecting a recording level in the **General > Recording** node of the **Recording Options** dialog box. The recording level you select depends on your needs and environment. The available levels are **HTML-based script** and **URL-based script**. For user interface information, see ["General > Recording Node" on page 200](#).

The following examples show scripts using the three recording levels:

### **HTML-based script**

Generates a separate step for each HTML user action. The steps are intuitive, but they do not reflect true emulation of the JavaScript code.

```
/* HTML-based mode - a script describing user actions*/  
...  
web_url("WebTours",  
        "URL=http://localhost/WebTours/",  
        "Resource=0",  
        "RecContentType=text/html",  
        "Referer=",  
        "Snapshot=t1.inf",  
        "Mode=HTML",  
        LAST);  
web_link("Click Here For Additional Restrictions",
```

```
    "Text=Click Here For Additional Restrictions",
    "Snapshot=t4.inf",
    LAST);
web_image("buttonhelp.gif",
    "Src=/images/buttonhelp.gif",
    "Snapshot=t5.inf",
    LAST);
...

```

## URL-based script

Records all browser requests and resources from the server that were sent due to the user's actions. Automatically records all HTTP resources as URL steps (**web\_url** statements). For normal browser recordings, it is not recommended to use the URL-based mode since is more prone to correlation related issues. However, if you are recording pages such as applets and non-browser applications, this mode is ideal.

URL-based scripts are not as intuitive as the HTML-based scripts since all actions are recorded as **web\_url** steps instead of **web\_link**, **web\_image**, and so on.

```
/* URL-based mode - only web_url functions */
...
web_url("spacer.gif",
    "URL=http://graphics.hplab.com/images/spacer.gif",
    "Resource=1",
    "RecContentType=image/gif",
    "Referer=",
    "Mode=HTTP",
    LAST);
web_url("calendar_functions.js",
    "URL=http://www.im.hplab.com/travelp/calendar_functions.js",
    "Resource=1",
    "RecContentType=application/x-javascript",
    "Referer=",
    "Mode=HTTP",
    LAST);
...

```

You can switch recording levels and advanced recording options while recording, provided that you are not recording a multi-protocol script. The option of combining recording levels is available to advanced users for performance testing.

You can also regenerate a script after recording, using a different method than the original recording. For example, if you record a script on an HTML-based level, you can regenerate it on a URL-based level. To regenerate a script, select **Record > Regenerate Script** and click **Options** to set the recording options for the regeneration.

## Serialization Overview

VuGen uses serialization when it encounters an unknown object during the recording, provided that the object supports serialization. An unknown object can be an input argument which was not

included by the filter and therefore its construction was not recorded. Serialization helps prevent compilation errors caused by the passing of an unknown argument to a method. If an object is serialized, it is often advisable to set a custom filter to record this object. For details, see ["How to Serialize Flex Scripts " on page 645](#).

## **Tips for Working with Event Listening and Recording**

It can sometimes be difficult to find the ideal listen and recording settings. When defining these settings, keep in mind the following guidelines:

- To record an event on an object, you must instruct VuGen to listen for the event, and to record the event when it occurs. You can listen for an event on a child object, even if a parent object contains the handler or behavior, or you can listen for an event on a parent object, even if the child object contains the handler or behavior.

However, you must enable recording for the event on the source object (the one on which the event actually occurs, regardless of which parent object contains the handler or behavior).

For example, suppose a table cell with an **onmouse over** event handler contains two images. When a user touches either of the images with the mouse pointer, the event bubbles up to the cell and includes information on which image was actually touched. You can record this mouse over event by:

- Setting **Listen** on the WebTable mouse over event to **If Handler** (so that VuGen "hears" the event when it occurs), while disabling recording on it, and then setting **Listen** on the Image mouse over event to **Never**, while setting its recording status to **Enable** (to record the mouse over event on the image after it is listened to at the WebTable level).
- Setting **Listen** on the Image mouse over event to **Always** (to listen for the mouse over event even though the image tag does not contain a behavior or handler), and setting the recording status on the Image object to **Enabled** (to record the mouse over event on the image).
- Instructing VuGen to listen for many events on many objects may lower performance, so try to limit listening settings to the required objects.
- In rare situations, listening to the object on which the event occurs (the source object) may interfere with the event.

## **Example of Click & Script Out of Context Recording**

In the following example, a script was regenerated with the out-of-context recording option enabled.

```
web_image_link("Search Flights Button",
    "Snapshot=t5.inf",
    DESCRIPTION,
    "Alt=Search Flights Button",
    "FrameName=navbar",
    ACTION,
    "ClickCoordinates=58,9",
    LAST);
```

```
web_add_cookie("MSO=SID=;1141052844; DOMAIN=localhost");
web_add_cookie("MTUserInfo=hash=;47=;firstName=;Joseph=;expDate=;
    %0A=;creditCard=;=;address1=;234%20Willow%20Drive=;
    lastName=;Marshall%0A=;address2=;San%20Jose%2FCA%2F94085=;
    username=;jojo; DOMAIN=localhost");
web_url("FormDateUpdate.class",
    "URL=http://localhost:1080/WebTours/FormDateUpdate.class",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "UserAgent=Mozilla/4.0 (Windows 2000 5.0) Java/1.4.2_08",
    "Mode=HTTP",
    LAST);
...
...
```

If you disable this option, VuGen does not generate code for the ActiveX controls and Java applets. In the following example, VuGen only generated the **web\_image\_link** function—not the **web\_url** functions containing the class files.

```
web_image_link("Search Flights Button",
    "Snapshot=t5.inf",
    DESCRIPTION,
    "Alt=Search Flights Button",
    "FrameName=navbar",
    ACTION,
    "ClickCoordinates=58,9",
    LAST);
```

For more information, see ["GUI Properties > Advanced Node" on page 219](#).

## Vuser Script Sections

Each Vuser script contains at least three sections: *vuser\_init*, one or more Actions, and *vuser\_end*. Before and during recording, you can select the section of the script into which VuGen will insert the recorded functions. The following table shows what to record into each section, and when each section is executed:

Script Section	Used when recording...	Is executed when...
<i>vuser_init</i>	a login to a server	the Vuser is initialized (loaded)
<i>Actions</i>	client activity	the Vuser is in <b>Running</b> status
<i>vuser_end</i>	a logoff procedure	the Vuser finishes or is stopped

When you run multiple iterations of a Vuser script, only the *Actions* sections of the script are repeated—the *vuser\_init* and *vuser\_end* sections are not repeated. For more information on the iteration settings, see ["General > Run Logic Node" on page 350](#).

You use the VuGen script editor to display and edit the contents of each of the script sections. You can display the contents of only a single section at a time. To display a section in the script editor, double-click the name of the section in the Solution Explorer.

When working with Vuser scripts that use Java classes, you place all your code in the Actions class. The Actions class contains three methods: init, action, and end. These methods correspond to the sections of scripts developed using other protocols—you insert initialization routines into the init method, client actions into the action method, and log off procedures in the end method.

For more information, see ["Java Vuser Protocol - Manually Programming Scripts" on page 667](#).

```
public class Actions{  
    public int init() {  
        return 0;}  
    public int action() {  
        return 0;}  
    public int end() {  
        return 0;}  
}
```

**Note:** Transaction Breakdown for Oracle DB is not available for actions recorded in the vuser\_init section.


## Script Section Structure Example

Every Vuser script contains three sections: *vuser\_init*, *Run (Actions)*, and *vuser\_end*. You can instruct a Vuser to repeat the *Run* section when you run the script. Each repetition is known as an *iteration*.

The *vuser\_init* and *vuser\_end* sections of a Vuser script are not repeated when you run multiple iterations.

When you run scripts with multiple actions, you can indicate how to execute the actions, and how the Vuser executes them:

In the following example, *Block0* performs a deposit, *Block1* performs a transfer, and *Block2* submits a balance request. The *Login* and *Logout* actions are common to the three blocks.



**Sequence.** You can set the order of actions within your script. You can also indicate whether to perform actions sequentially or randomly.

**Iterations.** In addition to setting the number of iterations for the entire *Run* section, you can set iterations for individual actions or action blocks. This is useful, for example, in emulating a commercial site where you perform many queries to locate a product, but only one purchase.

**Weighting.** For action blocks running their actions randomly, you can set the *weight* or percentage of each action within a block.

In most cases, the name of the header file corresponds to the prefix of the protocol. For example, Database functions that begin with an **Ird** prefix, are listed in the **Ird.h** file.

## Header Files

Header files commonly contain forward declarations of classes, subroutines, variables, and other identifiers. In most cases, the name of the header file corresponds to the prefix of the protocol. For example, Database functions that begin with an **Ird** prefix, are listed in the **Ird.h** file.

The following table lists the header files associated with the most commonly used protocols:

Protocol	File
Ajax (Click & Script)	<b>web_ajax.h</b>
Citrix	<b>ctrxfuncs.h</b>
COM/DCOM	<b>Irc.h</b>
Database	<b>Ird.h</b>
FTP	<b>mic_ftp.h</b>
General C function	<b>Irun.h</b>

Protocol	File
IMAP	<b>mic_imap.h</b>
LDAP	<b>mic_mldap.h</b>
MAPI	<b>mic_mapi.h</b>
Oracle NCA	<b>orafuncs.h</b>
POP3	<b>mic_pop3.h</b>
RDP	<b>Irrdp.h</b>
SAP GUI	<b>as_sapgui.h</b>
SAP (Click & Script)	<b>sap_api.h</b>
Siebel	<b>lrdsiebel.h</b>
SMTP	<b>mic_smtp.h</b>
Terminal Emulator	<b>Irrte.h</b>
WAP	<b>as_wap.h</b>
Web (HTML\HTTP)	<b>as_web.h</b>
Web (Click & Script)	<b>web_api.h</b>
Web Services	<b>wssoap.h</b>
Windows Sockets	<b>Irs.h</b>


## Providing Authentication Information

The following section applies only to multi-protocol scripts.


When recording a Web session that uses NTLM authentication, your server may require you to enter details such as a user name and password.

Initially, IE (Internet Explorer) tries to use the NT authentication information of the current user:

- If IE succeeds in logging in using this information and you record a script —then, at the end of the recording VuGen prompts you to enter a password. VuGen retrieves the user name and domain information automatically. If necessary, you can also edit the user name in the Web Recorder NTLM authentication dialog box.



- If IE is unable to log in with the current user's information, it prompts you to enter a user name and password using the standard browser authentication dialog box.



### Generating a `web_set_user` function

When performing NTLM authentication, VuGen adds a `web_set_user` function to the script.

- If the authentication succeeds, VuGen generates a `web_set_user` function with your user name, encrypted password, and host.

```
web_set_user("domain1\\dashwood",
             lr_decrypt("4042e3e7c8bbbcfde0f737f91f"),
             "sussex:8080");
```

- If you cancel the Web Recorder NTLM Authentication dialog box without entering information, VuGen generates a `web_set_user` function for you to edit manually.

```
web_set_user("domain1\\dashwood,  
    "Enter NTLM Password Here",  
    "sussex:8080");
```


**Note:** If you enter a password manually, it will appear in the script as-is, presenting a security issue. To encrypt the password, right-click the password and select **Encrypt string**. VuGen encrypts the string and generates an **Ir\_decrypt** function, used to decode the password during replay. For more information about encrypting strings, see "[Encrypting Text](#)" on page 403.

## Recording via a Proxy- Overview

VuGen allows you to record scripts using a LoadRunner proxy to resolve situations where you cannot install VuGen on the client machine. This may be the case with certain Linux machines, Mac OS machines, and mobile devices.

When using this option, the VuGen machine acts as a proxy server capturing all the traffic from the client machine to the target server. After the business process has been recorded VuGen creates a script.

The following diagram illustrates the basic workflow:



### Considerations for Recording via a Proxy:

- You can only create a Web - HTTP/HTML script when recording via a proxy.
- The client must allow proxy configurations, meaning, you must be able to specify the port and the address of the VuGen machine on the client device or machine.
- The client device or machine and the VuGen machine must be in the same network.

- Because VuGen is unable to bypass the browser's cache and history settings on the client machine, the client machine's browsing history must be deleted prior to recording the business process. This enables VuGen to accurately record your business process via a proxy.

## HTTP forwarding to multiple targets

If multiple target machines are present, the VuGen proxy can correctly forward data to the right target server according to the Host HTTP header.

## Forwarding to target server via Internet proxy server

You can configure the VuGen machine to establish a connection with your organization's internet proxy by selecting the **Remote Application via LoadRunner proxy** mode in the **Start Recording** dialog box.

For details, see "[Start Recording Dialog Box](#)" on page 266.

# How to Record a Script via a Proxy

This topic describes various methods for recording a script using a proxy server.

**Note:** In all use cases, the client machine and VuGen machine are in the same network.

## Use Case 1: You want to record a business process but you cannot install VuGen on the client machine or device.

### 1. Create a script

Select a **New script > Web - HTTP/HTML** script.

### 2. Start Recording

- From the **Start Recording** dialog box, select **Recording Mode > Record > Remote Application via LoadRunner Proxy**. For details, see "[Start Recording Dialog Box](#)" on page 266.
  - Specify the port on which the LoadRunner proxy will listen, by default, port 8888.
  - Check the **Display recording toolbar on client machine**. This allows you to see and interact with the recording toolbar on the client machine.
  - Click **Start Recording**.
- On the client machine, delete browser cache data which includes Temporary Internet Files and Cookies.
- ### 4. Configure proxy settings on client machine
- Configure the proxy settings to specify the VuGen machine as the proxy server. To do this, specify the machine address and port on which the LoadRunner proxy will listen.

Below are some sample configurations:

If your browser/OS is...	The path is...	Configuration
Internet Explorer	<ul style="list-style-type: none"><li>■ Internet Options &gt; Connections &gt; LAN Settings &gt; Proxy server</li><li>■ Control Panel and IE Tools &gt; Options menu</li></ul>	<ul style="list-style-type: none"><li>a. Select <b>Use a proxy server for your LAN</b></li><li>b. Specify <b>Port</b></li><li>c. Specify <b>Address</b></li></ul>
FireFox	Tools > Options > Network > Advanced > Connection > Settings...	<ul style="list-style-type: none"><li>a. Select <b>Manual proxy configuration</b></li><li>b. Specify <b>HTTP Proxy</b></li><li>c. Specify <b>Port</b></li><li>d. Check <b>Use this proxy server for all protocols</b></li></ul>

## 5. Record the business process

- a. Navigate to your application.
- b. Perform the steps of your business process you want to record.

## 6. Generate the script

- a. Select **Stop Recording** from either the **Recording Toolbar** on the client machine or the **Floating Recording Toolbar** on the VuGen machine.
- b. VuGen generates the script.

**Use Case 2: You want to record a business process but you cannot install VuGen on the machine (or device) running the application. The client machine requires a proxy to access the Internet.**

### 1. Create a script

Select a **New script > Web - HTTP/HTML** script.

### 2. Start Recording

- a. From the **Start Recording** dialog box, select **Recording Mode > Record > Remote application via LoadRunner Proxy**.

- b. If necessary, change the port on which the LoadRunner proxy will listen. The default is port 8888.
- c. Check **Display recording toolbar on client machine**. This allows you to see and interact with the recording toolbar on the client machine.
- d. A browser session is not launched on the local machine during a proxy recording. Therefore, a link is provided on the **Start Recording** dialog box to allow you to configure a connection to the internet proxy.

In Internet Explorer, select **Tools > Internet Options > Connections**. Click **LAN settings** and enter the port and address of the client machine's Internet proxy.

**Note:** The **Use automatic configuration script** option is not supported.

- e. Select **Start Recording**.
3. On the client machine, delete browser cache data which includes Temporary Internet Files and Cookies.

#### 4. Configure proxy settings on the client machine

On your client machine, configure the browser settings to use the VuGen's machine IP and port. The following table explains how to set the proxy settings.

If your browser/OS is...	The path is...	Configuration
Internet Explorer	<ul style="list-style-type: none"><li>▪ <b>Internet Options &gt; Connections &gt; LAN Settings &gt; Proxy server</b></li><li>▪ <b>Control Panel and IE Tools-&gt;Options menu</b></li></ul>	<ol style="list-style-type: none"><li>a. Select <b>Use a proxy server for your LAN</b></li><li>b. Specify <b>Port</b></li><li>c. Specify the VuGen IP in <b>Address</b></li></ol>
FireFox	<b>Tools &gt; Options &gt; Network &gt; Advanced &gt; Connection &gt; Settings...</b>	<ol style="list-style-type: none"><li>a. Select <b>Manual proxy configuration</b></li><li>b. Specify <b>HTTP Proxy</b></li><li>c. Specify <b>Port</b></li><li>d. Check <b>Use this proxy server for all protocols</b></li></ol>

## 5. Record the business process

- a. Navigate to your application.
- b. Perform the steps of your business process you want to record.

## 6. Generate the script

- a. Select **Stop Recording** from either the **Recording Toolbar** on the client machine or the **Floating Recording Toolbar** on the VuGen machine.
- b. VuGen generates the script.

### Use Case 3: Your application communicates using an SSL protocol.

1. You will need to import the LoadRunner SSL certificate to client machine.

**Note:** As an application developer, you can set certain policies on the server certificate when using SSL. However, only if the LoadRunner certificate conforms to the policy, can the client trust the server and the SSL connection be set.

2. To download the certificate, navigate to `http://<computer name of VuGen machine>:port/proxyroot.cer` or `http://<ip address of VuGen machine>:port/proxyroot.cer`.

**Note:** If you experience security restrictions, navigate to `http://<computer name VuGen machine>:port/proxyroot.dat` or `http://<ip address of VuGen machine>:port/proxyroot.dat`. After downloading the certificate, change the .dat extension back to .cer to import the certificate.

3. Import the SSL certificate. The following table provides examples of the path for various browsers.

If you browser is....	The path is...
Internet Explorer	<b>Internet Options &gt; Content &gt; Trusted Root Certificate Authorities &gt; Import</b>
FireFox	<b>Tool &gt; Options &gt; Advanced &gt; View Certificates &gt; Authorities &gt; Import</b>

## Use Case 4: You want to do a proxy recording of a local application that uses the system proxy, where VuGen and the client application are on the same machine.

1. Create a script

Select a **New script > Web - HTTP/HTML** script.

2. Set the Recording Option.

Open the recording options (**Recording > Recording Options**) and select the **HTTP Properties > Advanced** node. Enable the **Use the LoadRunner Proxy to record a local application**.

3. Start Recording

- a. Open the Start Recording dialog box (Ctrl +R).

- b. In the **Recording mode** section, select **Record: Web Browser**.

4. Perform the business process.

VuGen automatically resets the proxy back to its original setting after the recording. If the recording did not end in the normal way, for example, if your application crashed during recording, you may need to manually set the proxy back to its original value. **Internet Options > Connections > LAN Settings > Proxy server**.

If you are recording a Java application or a browser other than Internet Explorer, if the application is not using the system proxy settings, you will need to manually set the proxy of the application.

## How to Import Actions to a Script

For Vuser types that support multiple actions, you can import actions into your script from another Vuser script. You can import actions from Vusers of the same type only. Note that any parameters associated with the imported action will be merged with the script. The following steps describe how to import actions into the current script.

1. Select **Design > Action > Import Action**, or right-click the Solution Explorer and select **Import Action** from the right-click menu. The Import Action into VuGen Script dialog box opens.
2. Click **Browse** to select a Vuser script. A list of the script's actions appears in the **Actions to Import** section.
3. Select the actions you want to include and click **Import**. The imported action(s) are displayed in the **Solution Explorer**.

# How to Regenerate a Vuser Script

If you need to revert back to the script as it was when you originally recorded it, you can regenerate the script. This feature is ideal for debugging, or fixing a corrupted script. When you regenerate a script, VuGen removes all of the manually added enhancements to the recorded actions in the script. If you added parameters to your script, VuGen restores the original values. The parameter list, however, is not deleted; you can reinsert parameters that you created earlier. Note that regeneration only cleans up the recorded actions, but not those that were manually added.

This task describes how to regenerate a Vuser script.

## 1. Initialize the regeneration

Select **Record > Regenerate Script**. VuGen issues a warning indicating that all manual changes will be overwritten.

## 2. Modify regenerate options - optional

Click **Options** to open the **Regenerate Options** dialog box.

In a multiple protocol script, you can use the **General > Protocols** node to modify which protocols you want to record when the script is regenerated. For user interface details, see "[General > Protocol Node](#)" on page 200.

To change the Script options, select the **General > Script** node and select or clear the appropriate check box. For user interface details, see "[General > Script Node](#)" on page 203.

**Note:** If a Flex, Silverlight, or Java over HTTP Vuser script encounters errors during the code generation phase, VuGen will show the errors in the Error pane. This Error pane displays details about each error, as well as recommended actions. Follow the recommended actions and regenerate the script.

# Start Recording Dialog Box

This dialog box enables you to record your business process.

<b>To access</b>	<ul style="list-style-type: none"><li>• <b>VuGen &gt; Record &gt; Record</b></li><li>• [VuGen] <b>Start Recording</b> button</li></ul>
<b>Important information</b>	This dialog box is dynamic and changes according to the options you select as well as the protocol you are using.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• "<a href="#">How to Record a Vuser Script</a>" on page 175</li><li>• "<a href="#">Scripting Options</a>" on page 103</li><li>• "<a href="#">How to Record a Script via a Proxy</a>" on page 261</li></ul>

User interface elements are described below:

## All Protocols (except Java)

UI Element	Description
<b>Record into action</b>	The section into which you want to record. You can add your own action. Type the action name in the <b>Record into action</b> field and click <b>Add</b> . The new action is added to the script.
<b>Recording mode</b>	The mode used to record your business process. You can record: <ul style="list-style-type: none"><li>• <b>Web Browser.</b> For example Web and Oracle NCA record web applications.</li><li>• <b>Windows Application..</b> For example, Windows Socket Vusers records a windows application.</li><li>• <b>Remote Application via LoadRunner Proxy.</b> To record traffic when VuGen cannot run on the client machine. For example, Linux machines, Mac OS machines, and mobile devices. If you choose this mode, you can specify the following options:<ol style="list-style-type: none"><li>a. <b>LoadRunner proxy listens on port:</b> The port on which the LoadRunner proxy will listen.</li><li>b. <b>Display recording toolbar on client machine.</b> This allows you to interact with the recording toolbar on the client machine.</li></ol></li></ul>
<b>Application</b>	Select a browser or select a path of the Windows application to record.  The following browsers are supported: <ul style="list-style-type: none"><li>• Microsoft Internet Explorer</li><li>• Mozilla Firefox</li><li>• Google Chrome</li></ul> <p><b>Note:</b> To successfully record in Chrome or FireFox, close all windows and verify in the Windows Task Manager that there are no running Chrome or FireFox instances before you begin recording.</p>
<b>URL address</b>	The starting URL address. This option is displayed for internet applications only .
<b>Program arguments</b>	(Windows applications only) The command line arguments for the executable specified in <b>Recorded application</b> . For example, if you specify plus32.exe (recorded application) with the command line options peter@neptune, it connects the user Peter to the server Neptune when starting plus32.exe.

, continued


UI Element	Description
<b>Start Recording</b>	<p>You can record your business process either:</p> <ul style="list-style-type: none"><li>• <b>Immediately</b> - Recording starts as soon as you click the Start Recording button.</li><li>• <b>In delayed mode</b> - In the following instances, it may not be advisable to record immediately:<ul style="list-style-type: none"><li>▪ If you are recording multiple actions, in which case you only need to perform the startup in one action.</li><li>▪ In cases where you want to navigate to a specific point in the application before starting to record.</li><li>▪ If you are recording into an existing script.</li></ul></li></ul>
<b>Working directory</b>	For applications that require you to specify a working directory.
<b>Recording Options</b>	Opens the Recording Options dialog box. For user interface details, see <a href="#">"Recording Options" on page 176</a> .
<b>Start Recording button</b>	Begins to record your business process based on the option selected above: <b>Immediate</b> or <b>In delayed mode</b> .

## Java Protocols


UI Element	Description
<b>Record into action</b>	<b>The section into which you want to record.</b>
<b>Record:</b>	<ul style="list-style-type: none"> <li><b>Java applet</b> to record a Java applet through Sun's applet viewer.</li> <li><b>Java application</b> to record a Java application.</li> <li><b>Internet Explorer</b> to record an applet within a browser.</li> <li><b>Executable\Batch</b> to record an applet or application that is launched from within a batch file or the name of an executable file.</li> <li><b>Listener</b> to instruct VuGen to wait for the batch file that initializes the configuration and runs an application before recording. This mode requires you to define the system variable _JAVA_OPTIONS as <b>-Xrunjdhook</b> using jdk1.2.x and higher. (For JDK 1..x, define the environment variable <b>_classload_hook=JDKhook</b>. For JDK 1.6 set <b>_JAVA_OPTIONS</b> as <b>-agentlib:jdhook</b>.)</li> </ul>
<b>URL address</b>	The URL to start recording (for Internet Explorer recordings)
<b>Parameters</b>	Any additional parameters that your application requires.
<b>Main Class</b>	The <i>complete</i> path of the Java class with the main method. <b>Note:</b> This option is only present for <b>Java Application</b> type applications.
<b>Applet path</b>	This option is only present for Java applets.
<b>Internet Explorer path</b>	This option is only present for Internet Explorer type applications.
<b>Executable\Batch</b>	This option is only present for Executable\Batch type applications.
<b>Working directory</b>	A working directory is necessary only if your application must know the location of the working directory (for example, reading property files or writing log files).
<b>Recording Options</b>	Opens the Recording Options dialog box. For user interface details, see <a href="#">"Recording Options" on page 176</a> .

## Floating Recording Toolbar

The floating recording toolbar enables you to control the recording of Vuser scripts, and provides easy access to common script commands.

<b>UI example</b>	
<b>To access</b>	The floating recording toolbar appears when script recording begins.
<b>Important information</b>	<ul style="list-style-type: none"> <li>The floating recording toolbar is dockable. For details, see "<a href="#">VuGen Layouts - Overview</a>" on page 79.</li> <li>You can pin the toolbar with the  button.</li> <li>You can expand or collapse the toolbar with the  and  buttons.</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Create or Open a Vuser Script" on page 162</a>

User interface elements are described below:

UI Element	Description
	Continue recording the script after recording has been paused.
	Stop recording the script.
	Pause recording.
	Cancel the recording.
 Action	Select an action to record into.
 Action vuser_end	
	Create a new action to record into.
	Insert a <b>Start Transaction</b> step into your script. For details, see " <a href="#">"Transaction Overview" on page 397</a> ".
	Insert an <b>End Transaction</b> step into your script. For details, see " <a href="#">"Transaction Overview" on page 397</a> ".
	Insert a <b>Rendezvous point</b> step into your script. For details, see " <a href="#">"Rendezvous Points" on page 400</a> ".
	Insert a comment into your script.

UI Element	Description
	Insert a <b>Text Check</b> step into your script. For details, see " <a href="#">Text and Image Verification (Web Vuser Scripts) - Overview</a> " on page 820.
Recording... (14) 00:00:04	Displays: <ul style="list-style-type: none"><li>How many events have been recorded into your script.</li><li>The time elapsed since recording began, excluding time the script was paused.</li></ul>
	Pin or unpin the recording toolbar.
	Display or hide the toolbar buttons.
	Hide the recording toolbar. The toolbar reappears when you refresh or navigate to the next page. Hiding the toolbar may be useful if the toolbar covers controls in the application being operated, thereby preventing access to the controls.  <b>Note:</b> The Hide Toolbar button  appears for proxy recording only.

## Files Generated During Recording

Assuming that the recorded script has been given the name **vuser** and is stored under **c:\tmp**, the following is a list of the more important files that are generated after recording:

File Name	Details

<b>vuser.usr</b>	Contains information about the Vuser type, AUT, action files, and so forth.
<b>Example of vuser.usr file</b>	
	<pre>[General] Type=Oracle_NCA DefaultCfg=default.cfg BuildTarget= ParamRightBrace=&gt; ParamLeftBrace=&lt; NewFunctionHeader=0 MajorVersion=5 MinorVersion=0 ParameterFile=nca_test3.prm GlobalParameterFile= [Transactions] Connect= [Actions] vuser_init=init.c Actions=run.c vuser_end=end.c</pre>
<b>vuser.bak</b>	A copy of Vuser.usr before the last save operation.
<b>default.cfg</b>	Contains a listing of all run-time settings as defined in the VuGen application (think time, iterations, log, web).
<b>Example of default.cfg file</b>	
	<pre>[General] XlBridgeTimeout=120 [ThinkTime] Options=NOTHINK Factor=1 LimitFlag=0 Limit=1 [Iterations] NumOfIterations=1 IterationPace=IterationASAP StartEvery=60 RandomMin=60 RandomMax=90 [Log] LogOptions=LogBrief MsgClassData=0 MsgClassParameters=0 MsgClassFull=0</pre>
<b>vuser.asc</b>	The original recorded API calls.

<b>vuser.grd</b>	Contains the column headers for grids in database scripts.
<b>default.usp</b>	Contains the script's run logic, including how the actions sections run.
<b>init.c</b>	Exact copy of the Vuser_init function as seen in the VuGen main window.
<b>run.c</b>	Exact copy of the Action function as seen in the VuGen main window.
<b>end.c</b>	Exact copy of the Vuser_end function as seen in the VuGen main window.
<b>vdf.h</b>	A header file of C variable definitions used in the script.
<b>\Data</b>	The Data folder stores all of the recorded data used primarily as a backup. Once the data is in this folder, it is not touched or used. For example, Vuser.c is a copy of run.c.

## Troubleshooting and Limitations - Recording

This section describes troubleshooting and limitations for recording scripts with VuGen.

### Troubleshooting Missing Steps

**Issue:** Your script is missing steps you recorded.

You encounter the following warning in the **Output Pane > Code generation** tab:

Warning: One or more responses are missing or have missing packets. Therefore, a step may appear to be missing in the script.

This issue can be caused if the recording was stopped before all the responses were received.

If the script is generated from a .pcap file, check if the file has missing packets.

This can be caused when you click **Stop Recording** before all the traffic has been received.

**Steps to Resolve:** Record the script again. Make sure all pages and resources have been downloaded before clicking the **Stop Record** button.

### Recording on Internet Explorer 10

**Issue:** When recording on Internet Explorer (IE) 10, the browser uses cached pages, and may not record all of the steps.

**Steps to Resolve:** Each time you begin recording, configure IE 10 to always refresh Web pages from the server. After you begin a recording session, in IE, click F12 to open the Developer Tools pane. In this pane, usually located at the bottom of the browser window, select **Cache > Always refresh from server**.

### Certificate warning message

When you open VuGen as a non-administrator user, during the recording process you may see a certificate pop-up warning message. The message is automatically closed and does not affect the recording.

### McAfee protection software

McAfee protection software (such as Antivirus, especially the Host Intrusion Prevention component) may interfere with some LoadRunner components and block script recording.

**Workaround:** Remove the McAfee software. For details see the McAfee Knowledgebase Article: How to manually remove McAfee Agent 4.x at <https://kc.mcafee.com/corporate/index?page=content&id=KB65863>.

### Firefox as default browser

If Firefox is set as the default browser, the **Obtain the proxy settings from the default browser** option (Run-time Settings > Internet Protocol > Proxy) does not work, and a direct connection is used.

### 64-bit Recording

In general, 64-bit applications ported from a 32-bit client version should work identically to the 32-bit client. There is a small risk that new clients will use the power of native 64-bit applications. For example, when using 64-bit long types for Identifiers in DB tables, the identifier value will be cut and the query will fail.

The following guidelines apply:

- The environment for 64-bit recording must be a Windows 7 x64 or Windows 8 x64 (Windows 8 x64 added in Service Pack 11.52), and a 64-bit Application Under Test (AUT).
- Recording on 64-bit operating system for 32 and 64-bit applications (running as a 64-bit application) is supported.
- You cannot record a page requiring a client certificate with 64-bit version of Internet Explorer.
- Replay is only supported for 32-bit.
- For the Java Over HTTP protocol: JVM 32-bit is required for replay.
- For the .NET protocol: There are two available 64-bit types for .NET applications (AnyCPU and pure 64-bit). LoadRunner only supports AnyCPU. There is currently no solution for pure 64-bit applications.


For replay, LoadRunner uses the same AnyCPU dlls that were used for Recording.

- **Note:** With LoadRunner 11.50 and higher, .NET Framework 4 should be installed. This package carries both versions of the libraries for 32 and 64-bit systems.
- Oracle 2-Tier: Both 32-bit and 64-bit clients need to be installed (the 32-bit client is required for replay).

## Correlation Studio

### Correlation Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the third step, correlating a Vuser script.



Correlation is used when a recorded script includes a dynamic value (such as a session ID) and therefore cannot be successfully replayed. To resolve this, you convert the dynamic value into a variable—thereby enabling your script to replay successfully.

For example, many applications and Web sites use the current date and time to identify a session. If you try to replay a script that was recorded on such a site, the script may fail because the current time is different from the recorded time. Correlating the data enables you to save the dynamic data and use it throughout the scenario run.

When a correlation is created, VuGen adds a function that extracts the dynamic value to a parameter. Appropriate occurrences of the original value are replaced with a parameter.

For details, see "[Correlation Tab \[Design Studio\] Overview](#)" below .

## Correlation Tab [Design Studio] Overview


The Correlation tab enables you to correlate and manage dynamic values in your web-based Vuser scripts. To learn more about correlation concepts, see "[Correlation Overview](#)" on the previous page.

With the **Correlation tab** you can:

- Scan for correlations using rules, record based, and replay based engines
- Correlate both raw and formatted data
- Add and edit rules
- Undo correlations
- Review details pertaining to a specific dynamic value in a snapshot

When you record a script using a web-based protocol, many of the values change dynamically each time a request is sent to the server. An example of a dynamic value is a `sessionId` which may include a date and time stamp of when the web session was opened. To learn more, see "[How to Correlate Scripts Using Design Studio](#)" on page 280

The following flow chart illustrates the process for correlating values in your script using the Correlation tab:



As you can see from the flow chart, the Correlation tab scans for dynamic values using different processes.

## Correlation Types

Design Studio uses three processes to automatically find dynamic values that may need to be correlated.

- Rules

Design Studio first scans for dynamic values that are defined by rules, if the rules scan has been enabled. To learn more, see "[Correlation Rules](#)" on the next page.

- Record

Design Studio scans for dynamic values after code generation. This method can find a significant percentage of dynamic values in your script.

- Replay

Design Studio scans for dynamic values after replay. This method may need to be repeated several times.

You can select which scan types the Correlation tab should use by configuring **Recording Option > Correlations > Configuration**. In general, it is recommended to enable all scan types.

The following table explains the expected behavior at various script states:

Script State when opening the Correlation tab	Behavior in the Correlation tab <b>(All scan types enabled)</b>
Script contains recorded data.	<p>When Design Studio is opened, it will scan for rule and record based correlations.</p> <p>You can then replay and scan for replay based correlations. Repeat this process until the Design Studio no longer finds new correlations.</p>
Script contains recorded data and has been replayed.	<p>When the Correlation tab is opened, it will scan for all correlation types.</p> <p>You can then replay and scan for additional replay based correlations. Repeat this process until Design Studio no longer finds new correlations.</p>

## Correlation Rules

If you know the dynamic values that need to be correlated before recording, you can create correlation rules that will automatically identify those values while you record. If "Automatically apply correlation rules" is selected in the **Recording Options > Correlations > Configuration** node, values found based on rules will automatically be correlated. Additionally, there are some correlation rules that come pre-defined in VuGen for supported application servers. You can enable or disable rules in "[Correlations > Rules](#)" on page 186.

## Snapshot Details and Occurrences

Design Studio provides details on each snapshot step that contains dynamic values. These details can help you determine which values to correlate in your script. In addition to the snapshot details, the Correlation tab, displays all occurrences of the dynamic value in your script. You can select specific occurrences to correlate or correlate all. For details, see "["Design Studio \[Correlation Tab\] Dialog Box"](#) on page 312.

## Determining Which Values to Correlate

Once you generate a list of differences, you need to determine which ones to correlate. If you mistakenly correlate a difference that did not require correlation, your replay may be adversely affected.

The following strings most probably require correlation:

- **Login string.** A login string with dynamic data such as a session ID or a timestamp.
- **Date/Time Stamp.** Any string using a date or time stamp, or other user credentials.
- **Common Prefix.** A common prefix, such as **SessionID** or **CustomerID**, followed by a string of characters.

If you are in doubt whether a difference should be correlated, correlate only that difference and then run your script. Check the Replay log to see if the issue was resolved.

You should also correlate differences in which some of the recorded and replayed strings are identical, but others differ. For example, SessionID strings with identical prefixes and suffixes, but different characters in between, should be correlated.

## Modifying Saved Parameters

After you save a value to a parameter, you may need to modify it before using it in your script. If you need to perform arithmetical operations on a parameter, you must change it from a string to an integer using the **atoi** or **atol** C functions. After you modify the value as an integer, you must convert it back to a string to use the new variable in your script.

In the following WinSock example, the data at offset 67 was saved to the parameter, **param1**. Using **atol**, VuGen converted the string to a long integer. After increasing the value of **param1** by one, VuGen converted it back to a string using **sprintf** and saved it as a new string, **new\_param1**. The value of the parameter is displayed using **lr\_output\_message**. This new value may be used at a later point in the script.

```
lrs_receive("socket2", "buf47", LrsLastArg);lrs_save_param("socket2",
    NULL, "param1", 67, 5);
lr_output_message ("param1: %s", lr_eval_string("<param1>"));
sprintf(new_param1, "value=%ld", atol(lr_eval_string("<param1>")) + 1);
lr_output_message("ID Number:\"%s\" lr_eval_string("new_param1"));
```

## Correlation vs. Parameterization

Parameterization is used when you want to take a value and turn it into a variable in order to make your script more realistic. For example, if you are filling out a form on a website, you may want to vary the value entered for a particular field.

Correlation is used when a recorded script includes a dynamic value (such as a session ID) and cannot replay. To resolve this, you make the dynamic value into a variable thereby enabling your script to replay successfully.

## Wdiff Correlation Utility

The Wdiff Utility lets you compare recorded Vuser scripts and replay results to determine which values need to be correlated.

To use *WDiff* effectively, you record the identical operation twice, and compare the scripts (or data files for WinSock). WDiff displays differences in yellow. Note that not all differences indicate a value to correlate. For example, certain receive buffers that indicate the time of execution do not require correlation.

For task details, see "[How to Search for Values that Need Correlation](#)" on page 302.

## Correlating Java Scripts

VuGen's Java recorder attempts to automatically correlate statements in the generated script. It only performs correlation on Java objects. When it encounters a Java primitive (byte, character, boolean, integer, float, double, short, and long) during recording, the argument values appear in the

script without association to variables. VuGen automatically correlates all objects, arrays of objects, and arrays of primitives. Note that Java arrays and strings are also considered objects.

VuGen employs several levels of correlation: Standard, Enhanced, Strings. You enable or disable correlation from the Recording options. An additional method of Serialization can be used to handle scripts where none of the former methods can be applied.

#### Standard Correlation

Standard correlation refers to the automatic correlation performed during recording for simple objects, excluding object arrays, vectors, and container constructs.

When the recorded application invokes a method that returns an object, VuGen's correlation mechanism records these objects. When you run the script, VuGen compares the generated objects to the recorded objects. If the objects match, the same object is used. The following example shows two CORBA objects my\_bank and my\_account. The first object, my\_bank, is invoked; the second object, my\_account, is correlated and passed as a parameter in final line of the segment:

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        Bank my_bank = bankHelper.bind("bank", "shunra");  
        Account my_account = accountHelper.bind("account", "shunra");  
        my_bank.remove_account(my_account);  
    }  
:  
}
```

#### Advanced Correlation

Advanced or **deep** correlation refers to the automatic correlation performed during recording for complex objects, such as object arrays and CORBA container constructs.

The deep correlation mechanism handles CORBA constructs (structures, unions, sequences, arrays, holders, `any's) as containers. This allows it to reference inner members of containers, additional objects, or different containers. Whenever an object is invoked or passed as a parameter, it is also compared against the inner members of the containers.

In the following example, VuGen performs deep correlation by referencing an element of an array. The remove\_account object receives an account object as a parameter. During recording, the correlation mechanism searches the returned array my\_accounts and determines that its sixth element should be passed as a parameter.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        my_banks[] = bankHelper.bind("banks", "shunra");  
        my_accounts[] = accountHelper.bind("accounts", "shunra");  
        my_banks[2].remove_account(my_accounts[6]);  
    }  
:  
}
```

The following segment further illustrates enhanced correlation. The script invokes the send\_letter object that received an address type argument. The correlation mechanism retrieves the inner member, address, in the sixth element of the my\_accounts array.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        my_banks = bankHelper.bind("bank", "shunra");  
        my_accounts = accountHelper.bind("account", "shunra");  
        my_banks[2].send_letter(my_accounts[6].address);  
    }  
:  
}
```

#### String Correlation

String correlation refers to the representation of a recorded value as an actual string or a variable. When you disable string correlation (the default setting), the actual recorded value of the string is indicated explicitly within the script. When you enable string correlation, it creates a variable for each string, allowing you to use it at a later point in the script.

In the following segment, string correlation is enabled—you store the value returned from the get\_id method in a string type variable for use later on in the script.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        my_bank = bankHelper.bind("bank", "shunra");  
        my_account1 = accountHelper.bind("account1", "shunra");  
        my_account2 = accountHelper.bind("account2", "shunra");  
        string = my_account1.get_id();  
        string2 = my_account2.get_id();  
        my_bank.transfer_money(string, string2);  
    }  
:  
}
```

## How to Correlate Scripts Using Design Studio

This topic describes how to use the Correlation tab to correlate Vuser scripts.

### Prerequisites


1. Record a script using one of the following protocols:
  - Web HTTP/HTML
  - Flex
  - RTMP/RTMPT
  - Citrix

- SAP Web
- Oracle NCA

**Note:** You can only correlate the Web HTTP/HTML steps within your Oracle NCA script and the Web HTTP/HTML protocol must be active. To activate, select **Recording Options > Protocol > Active Protocols > Web HTTP/HTML**.

For additional information on manual correlation, see "[How to Correlate Scripts - Oracle NCA](#)" on page 292

2. Verify that **Record > Recording Options > Correlations > Configuration** has all scan types enabled.



## Using the Correlation tab

1. **Initial Scan:** Click the **Design Studio** button. This will open the Design Studio dialog box which will scan for response (or record based) correlations and apply correlation rules. The progress bar in the dialog box indicates if the initial scan was successful.

For details on the Correlation tab, see "[Correlation Tab \[Design Studio\] Overview](#)" on page 275.

2. You can select which values you would like to correlate by highlighting the value in the grid and clicking the **Correlate** button.

When a value is correlated, VuGen adds a `web_reg_save_param_*` function, and saves the original value in a comment in the script.

You can examine the details of the correlation by expanding the Details Chevron in the dialog box. For details, see "[Design Studio \[Correlation Tab\] Dialog Box](#)" on page 312.

For details on the Correlation tab, see "[Correlation Tab \[Design Studio\] Overview](#)" on page 275.

3. You can click the **Add as Rule** button to add a rule type . In addition, you can click the **Edit rule** button to view and edit the corresponding rule if the dynamic value was correlated by a rule. For details, see [Recording Options > Correlation > Rules](#).

4. **Replay and Scan:** After you have correlated the values, click the **Replay and Scan** button. The Correlation tab progress bar indicates if additional correlations have been found. Again, you can select which values you would like to correlate by highlighting the value in the grid and clicking the **Correlate** button. You may need to repeat this step several times.
5. **Design Studio Scan Complete:** When Design Studio no longer finds new correlations, the progress bar will display "Design Studio Scan Complete".

**Tip:** If Design Studio does not resolve all correlation-based errors, try to resolve them using manual correlation. For details, see "[How To Manually Correlate Scripts](#)" below.

## How To Manually Correlate Scripts

If the scan for correlation did not resolve all correlation-based errors in your script, you can attempt to manually correlate your script as follows:

1. **Search for values that need correlation manually.** There are a number of ways to manually search for values that need correlation. For details, see "[How to Search for Values that Need Correlation](#)" on page 302.
2. **Correlate the value.**

Select one of the following methods:

- **Correlate from snapshots.** Highlight the value to correlate, right-click, and select **Create Correlation**.

When a value is correlated, VuGen adds the correlation parameter and saves the original value in a comment in the script.

```
252 | /* Correlation comment - Do not change! Original value='1' Name ='CorrelationParameter' Type ='Manual' */
253 | lrc_save_rs_param(_Recordset_45,
254 |   1,
255 |   2,
256 |   0,
257 |   "CorrelationParameter");
```

- **Manually add correlation functions.** Manually insert the relevant correlation functions into your script. For details, see "[How to Correlate Scripts - Web \(Manually\)](#)" on page 286.

## How to Correlate Scripts From a Snapshot

The following steps describe how to correlate scripts from a snapshot.


This task applies to the following protocols:

- Database Protocols
- RTMP
- COM Protocols

#### 1. Open the Output Pane

Select **View > Output** to display the output tabs at the bottom of the window. Check for errors in the Replay tab. Often, these errors can be corrected by correlation.

#### 2. Select the relevant step in the **Step Navigator**, and view the step in the **Snapshot pane**. Right click the value in the snapshot and select **Create correlation**. This will open the **Design Studio** window.



3. You can select the value you would like to correlate by highlighting it in the grid and clicking the **Correlate** button.
4. When a value is correlated, VuGen adds the correlation parameter, and saves the original value in a comment in the script.

```
252 /* Correlation comment - Do not change! Original value='1' Name ='CorrelationParameter' Type ='Manual' */
253 lrc_save_rs_param(_Recordset_45,
254     1,
255     2,
256     0,
257     "CorrelationParameter1");
```

## Correlating Winsock Scripts

VuGen's Design Studio provides a user interface for correlating Vuser scripts. Correlation is required when working with dynamic data. A common issue with Winsock Vuser scripts is dynamic ports—ports whose numbers are assigned dynamically. While certain applications always use the same port, others use the next available port. If you try to replay a script and the recorded port is no

longer available, your script will fail to replay. To overcome this issue, you must perform correlation—save the actual run-time values and use them within the script.

VuGen uses **Irs\_save\_param** and **Irs\_save\_searched\_string** functions correlate Winsock scripts. This means that it stores the data that is received for use in a later point within the script. Since correlation stores the received data, it applies only to Receive buffers and not to Send buffers. The recommended procedure is to select a string of dynamic data within the Receive buffer that you want to correlate. Use that same parameter in a subsequent Send buffer.

## Correlating a Winsock script

You use the Snapshot pane to begin correlating Winsock Vuser scripts. Both the Text and the Hex tabs in the Snapshot pane have the correlating functionality.

1. In the Snapshot pane, select the data that you want to correlate.
2. Right-click in the selection, and select **Create Correlation** or **Create Boundary Correlation**. The Design Studio opens and displays the Correlation tab.

Note that you can click the number of occurrences in the **Replace/Found** column to enable you to choose the exact occurrences that you want to correlate.
3. Click the **Details** bar to display details about the correlation.
4. Make sure that the **Original Snapshot Step** tab is visible. Notice that the type is either **Data Range** or **Boundary Based**.
5. Click **Correlate** to perform the correlation of the Vuser script.
6. Click **Close** to close the Design Studio. Notice that VuGen has inserted the appropriate correlation functions and comments into the script.

For further details on how to use the Design Studio, see "["Correlation Tab \[Design Studio\] Overview"](#) on page 275.

## Parameterization vs Correlation

This type of correlation should not be confused with simple parameterization. Simple parameterization (**Design > Parameters > Create New Parameter**) applies only to data within Send buffers. You set up a parameter and assign it several values. VuGen uses the different values in each of the script runs or iterations. For further details, see "["Correlation vs. Parameterization"](#) on page 278.

For details on how to manually correlate a Winsock Vuser script, see "["How to Correlate Scripts - Winsock \(Manually\)"](#) below.

# How to Correlate Scripts - Winsock (Manually)

This topic describes how to use the Editor to manually correlate a Winsock Vuser script.

1. Insert the **Irs\_save\_param\_ex** statement into your script at the point where you want to save

the buffer contents. You can save user, static, or received type buffers.

```
lrs_save_param_ex (socket, type, buffer, offset, length, encoding, parameter);
```

2. View the buffer contents by selecting **data.ws** in the Action Pane of the main VuGen window (displayed by default in the Editor). Locate the data that you want to replace with the contents of the saved buffer. Replace all instances of the value with the parameter name in parameter braces. The default parameter braces are brackets (< > or ()). You can modify the parameter braces in the **Tools > Options > Scripting > Parameters** tab.

In the following example, a user performed a telnet session. The user used a ps command to determine the process ID (PID), and killed an application based on that PID.

```
frodo:/u/jay>ps
    PID TTY      TIME CMD
14602 pts/18    0:00 clock
14569 pts/18    0:03 tcsh
frodo:/u/jay>kill 14602
[3]   Exit 1          clock
frodo:/u/jay>
```

During execution, the PID of the procedure is different (Linux assigns unique PIDs for every execution), so killing the recorded PID will be ineffective. To overcome this problem, use **lrs\_save\_param\_ex** to save the current PID to a parameter. Replace the constant with the parameter.

3. In the **data.ws** file, determine the buffer in which the data was received, buf47.

```
recv buf47 98
  "\r"
  "\x00"
  "\r\n"
  "    PID TTY      TIME CMD\r\n"
  " 14602 pts/18    0:00 clock\r\n"
  " 14569 pts/18    0:02 tcsh\r\n"
  "frodo:/u/jay>
.
.
.
send buf58
  "kill 14602"
```

4. In the Actions section, determine the socket used by buf47. In this example it is socket1.

```
lrs_receive("socket1", "buf47", LrsLastArg);
```

5. Determine the offset and length of the data string to save. The offset of the **PID** is 11 and its length is 5 bytes. For additional information about displaying the data, see "["Data Buffers" on page 963](#).

6. Insert an **lrs\_save\_param\_ex** function in the Action section, after the **lrs\_receive** for the relevant buffer. In this instance, the buffer is **buf47**. The PID is saved to a parameter called **param1**. Print the parameter to the output using **lr\_output\_message**.

```
lrs_receive("socket1", "buf79", LrsLastArg);
lrs_save_param("socket1", "user", buf47, 11, 5, ascii, param1);

lr_output_message ("param1: %s", lr_eval_string("<param1>"));
lr_think_time(10);
lrs_send("socket1", "buf80", LrsLastArg);
```

7. In the data file, data.ws, determine the data that needs to be replaced with a parameter, the PID.

```
send buf58
"kill 14602"
```

8. Replace the value with the parameter, enclosed in angle brackets.

```
send buf58
"kill <param1>"
```

## How to Correlate Scripts - Web (Manually)

This task describes how to correlate web scripts manually by modifying the code.

### 1. Locate the string and its details

Identify the statement that contains dynamic data and the patterns that characterize the locations of the data. These patterns may be boundaries or xpaths.

#### a. Identify Patterns using Boundaries

Use these guidelines to determine and set the boundaries of the dynamic data:

- Analyze the location of the dynamic data within the HTTP response.
- Identify the string that is immediately to the left of the dynamic data. This string defines the left boundary of the dynamic data.
- Identify the string that is immediately to the right of the dynamic data. This string defines the right boundary of the dynamic data.
- The right and left boundaries should be as unique as possible to better locate the strings.
- **web\_reg\_save\_param\_ex** looks for the characters between (but not including) the specified boundaries and saves the information beginning one byte after the left boundary and ending one byte before the right boundary. **web\_reg\_save\_param\_ex** does not support embedded boundary characters.

For example, if the input buffer is {a{b{c} and "{" is specified as a left boundary, and "}"

as a right boundary, the first instance is c and there are no further instances—it found the right and left boundaries but it does not allow embedded boundaries, so "c" is the only valid match.

By default, the maximum length of any boundary string is 256 characters. Include a **web\_set\_max\_html\_param\_len** function in your script to increase the maximum permitted length. For example, the following function increases the maximum length to 1024 characters:

These length restrictions do not apply where either the left or right boundaries are blank.

b. **Identify Patterns using Xpaths**

Use the snapshot pane to manually search for the xpath of the desired string.

By default, the maximum length of any boundary string is 256 characters. Include a **web\_set\_max\_html\_param\_len** function in your script to increase the maximum permitted length. For example, the following function increases the maximum length to 1024 characters:

These length restrictions do not apply where either the left or right boundaries are blank.

2. **Add web\_reg\_save\_param\_\* function**

Add a **web\_reg\_save\_param\_ex** or **web\_reg\_save\_param\_xpath** function into the script before the statement that contains the dynamic data.

a. **web\_reg\_save\_param\_ex**

This function searches server responses in web steps for the left boundary following by the string and the right boundary and saves the string to a parameter named in the function's argument. After finding the specified number of occurrences, **web\_reg\_save\_param\_ex** does not search any more responses. For more information, see the Function Reference ([Help > Function Reference](#)).

b. **web\_reg\_save\_param\_xpath**

This function searches server responses in web steps for a specified xpath. The string located in specified xpath is saved to a parameter named in the function's argument. For more information, see the Function Reference ([Help > Function Reference](#)).

3. **Replace data with parameter**

Select **Edit > Replace** from the VuGen main window to display the Search and Replace dialog box. Search the entire script for the dynamic data and replace it with a parameter. Give the parameter any name and enclose it with braces: {param\_name}. You can include a maximum of 64 parameters per script.

## How to Correlate Scripts - Siebel Protocol

The following steps describe how to correlate Siebel Web Vuser scripts.

## Correlation Library

To assist you with correlation, Siebel has released a correlation library file as part of the Siebel Application Server version 7.7. This library is available only through Siebel. The library file, **ssdtcorr.dll**, is located under the siebsrvr\bin folder for Windows and under siebsrvr/lib for Linux installations.

The library file, **ssdtcorr.dll**, must be available to all machines where a Load Generator or Controller reside. Support for this library requires VuGen 8.0 and higher. The following steps describe how to enable correlation with this library.

1. Copy the DLL file into the bin folder of the product installation.
2. Open a multi-protocol script using the **Siebel-Web** Vuser type.
3. Enable UTF-8 support in the **Recording Options > HTTP Properties > Advanced** node.
4. Open the recording option's Correlation node and click **Import**. Import the rules file, **WebSiebel77Correlation.cor**, from the \dat\webrulesdefaultsetting folder. If you are prompted with warnings, click **Override**.

To revert to the default correlation, delete all of the Siebel rules and click **Use Defaults**.

When using the Siebel correlation library, verify that the SWE count rules (where the left boundary contains the **SWEC** string) are not disabled.

## Correlation Rules

VuGen's native built-in rules for the Siebel server detect the Siebel server variables and strings, automatically saving them for use at a later point within the script. The rules list the boundary criteria that are unique for Siebel server strings.


When VuGen detects a match using the boundary criteria, it saves the value between the boundaries to a parameter. The value can be a simple variable or a public function.

In normal situations, you do not need to disable any rules. In some cases, however, you may want to disable rules that do not apply. For example, disable Japanese content check rules when testing English-only applications.

Another reason to disable a rule is if the Controller explicitly requires an error condition to be generated. View the rule properties in the recording options and determine the conditions necessary for your application.

### Simple Variable Correlation

In the following example, the left boundary criteria is `_sn=`. For every instance of `_sn=` in the left boundary and `;` in the right, VuGen creates a parameter with the **Siebel\_sn\_cookie** prefix.



In the following example, VuGen detected the \_sn boundary. It saved the parameter to Siebel\_sn\_cookie6 and used it in the web\_url function.

```
/* Registering parameter(s) from source
web_reg_save_param("Siebel_sn_cookie6",
"LB/IC=_sn=",
"RB/IC=;",
"Ord=1",
"Search=headers",
"RelFrameId=1",
LAST);
...
web_url("start.swe_3",
"URL=http://cannon.hplab.com/callcenter_enu/start.swe?SWECmd=GotoPostedAction=;S
WEDIC=true=;_sn={Siebel_sn_cookie6}=;SWEC={Siebel_SWECount}=;SWEFrame=top._swecl
ient=;SWECS=true",
"TargetFrame=",
"Resource=0",
"RecContentType=text/html",
"Referer=http://cannon.hplab.com/callcenter_enu/start.swe?SWECmd=GetCachedFrame
=;_sn={Siebel_sn_cookie6}=;SWEC={Siebel_SWECount}=;SWEFrame=top._swe",
"Snapshot=t4.inf",
"Mode=HTML",
LAST);
```

### Function Correlation

In certain instances, the boundary match is a function. Functions generally use an array to store the run-time values. In order to correlate these values, VuGen parses the array and saves each argument to a separate parameter using the following format:

```
<parameter_name> = <recorded_value> (display_name)
```

The display name is the text that appears next to the value, in the Siebel Application.

VuGen inserts a comment block with all of the parameter definitions.

```
/* Registering parameter(s) from source task id 159
   // {Siebel_Star_Array_Op33_7} = ""
   // {Siebel_Star_Array_Op33_6} = "1-231"
   // {Siebel_Star_Array_Op33_2} = ""
   // {Siebel_Star_Array_Op33_8} = "Opportunity"
   // {Siebel_Star_Array_Op33_5} = "06/26/2003 19:55:23"
   // {Siebel_Star_Array_Op33_4} = "06/26/2003 19:55:23"
   // {Siebel_Star_Array_Op33_3} = ""
   // {Siebel_Star_Array_Op33_1} = "test camp"
   // {Siebel_Star_Array_Op33_9} = ""
   // {Siebel_Star_Array_Op33_rowid} = "1-6F"
   // */
```

In addition, when encountering a function, VuGen generates a new parameter for **web\_reg\_save\_param**, **AutoCorrelationFunction**. VuGen also determines the prefix of the parameters and uses it as the parameter name. In the following example, the prefix is **Siebel\_Star\_Array\_Op33**.

```
web_reg_save_param("Siebel_Star_Array_Op33",
   "LB/IC=`v`",
   "RB/IC=`",
   "Ord=1",
   "Search=Body",
   "RelFrameId=1",
   "AutoCorrelationFunction=f1CorrelationCallbackParseStarArray",
   LAST);
```

VuGen uses the parameters at a later point within the script. In the following example, the parameter is called in **web\_submit\_data**.

```
web_submit_data("start.swe_14", "Action=http://cannon.hplab.com/callcenter_enu/start.swe",
   "Method=POST", "RecContentType=text/html", "Referer=", "Snapshot=t15.inf", "Mode=HTML",
   ITEMDATA, "Name=SWECLK", "Value=1", ENDITEM, "Name=SWEField", "Value=s_2_1_13_0",
   ENDITEM, "Name=SWER", "Value=0", ENDITEM, "Name=SWESP", "Value=false",
   ENDITEM, "Name=s_2_2_29_0", "Value={Siebel_Star_Array_Op33_1}", ENDITEM, "Name=s_2_2_30_0",
   "Value={Siebel_Star_Array_Op33_2}", ENDITEM, "Name=s_2_2_36_0", "Value=
   {Siebel_Star_Array_Op33_3}", ENDITEM, ...
```

During replay, Vusers do a callback to the public function, using the array elements that were saved as parameters.

**Note:** Correlation for the **SWEC** parameter is not done through the correlation rules. VuGen handles it automatically with a built-in detection mechanism. For more information, see **SWEC Correlation**.

## SWEC Correlation

SWEC is a parameter used by Siebel servers representing the number of user clicks. The SWEC parameter usually appears as an argument of a URL or a POST statement. For example:

```
GET /callcenter_enu/start.swe?SWECmd=GetCachedFrame=_sn=2-mOTFXHWBAAGb5Xzv9Ls2Z
45QvxGQnOnPVtX6vnfUU_=;SWEC=1_=;SWEFrame=top._swe._sweapp HTTP/1.1
```

or

```
POST /callcenter_enu/start.swe HTTP/1.1
...
\r\n\r\n
SWERPC=1=;SWEC=0=_sn=2-mOTFXHWBAAGb5Xzv9Ls2Z45QvxGQnOnPVtX6vnfUU_=;SWEcmd=InvokeMethod...
```

VuGen handles the changes of the SWEC by incrementing a counter before each relevant step. VuGen stores the current value of the SWEC in a separate variable (`Siebel_SWECOUNT_var`). Before each step, VuGen saves the counter's value to a VuGen parameter (`Siebel_SWECOUNT`).

In the following example, `web_submit_data` uses the dynamic value of the SWEC parameter, `Siebel_SWECOUNT`.

```
Siebel_SWECOUNT_var += 1;
lr_save_int(Siebel_SWECOUNT_var, "Siebel_SWECOUNT");
web_submit_data("start.swe_8",
    "Action=http://cannon.hplab.com/callcenter_enu/start.swe",
    "Method=POST",
    "TargetFrame=",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t9.inf",
    "Mode=HTML",
    "EncodeAtSign=YES",
    ITEMDATA,
    "Name=SWERPC", "Value=1", ENDITEM,
    "Name=SWEC", "Value={Siebel_SWECOUNT}", ENDITEM,
    "Name=SWEcmd", "Value=InvokeMethod", ENDITEM,
    "Name=SWEService", "Value=SWE Command Manager", ENDITEM,
    "Name=SWEMethod", "Value=BatchCanInvoke", ENDITEM,
    "Name=SWEIPS",...
    LAST);
```

Note that the SWEC parameter may also appear in the referrer URL. However, its value in the referrer URL usually differs from its value in the requested URL. VuGen handles this automatically.

## Correlate SWECOUNT Parameters

The SWECOUNT parameter value is usually a small number consisting of one or two digits. It is often difficult to determine where to replace the recorded value with a parameter.

In the `web_submit_data` function, VuGen only replaces it in the SWEC field.

In URLs, VuGen only replaces the value when it appears after the strings "SWEC=" or "SWEC`".

The parameter name for all the SWECOUNT correlations is the same.

## Correlate ROWID Parameters

In certain cases, the `rowid` is preceded by its length, encoded in hexadecimal format. Since this length can change, this value must be correlated.

For example, the following string is comprised of a length value and RowID, xxx6\_1-4ABCyyy, where 6 is the length, and 1-4ABC is the RowID.

If you define parameters to correlate the string as

```
xxx{rowid_Length}_{rowid}yyy
```

then using this enhanced correlation, VuGen generates the following function before the string:

```
web_save_param_length("rowid", LAST);
```

This function gets the value of **rowid**, and saves its length into the parameter **rowid\_Length** in hexadecimal format.

### Correlate SWET (timestamp) Parameters

The SWETS value in the script, is the number of milliseconds since midnight January 1st, 1970.

VuGen replaces all non-empty timestamps in the script, with the parameter {SiebelTimeStamp}. Before saving a value to this parameter, VuGen generates the following function:

```
web_save_timestamp_param("SiebelTimeStamp", LAST);
```

This function saves the current timestamp to the **SiebelTimeStamp** parameter.

## How to Correlate Scripts - Oracle NCA

The following steps describe different items in Oracle NCA scripts that may need correlation.

### Correlate Statements for Load Balancing

VuGen supports load balancing for multiple application servers. You correlate the HTTP return values with the **nca\_connect\_server** parameters. The Vuser then connects to the relevant server during test execution, applying load balancing. The following steps describe how to correlate statements for load balancing.

#### 1. Record a multi-protocol script.

Record a multi-protocol script for Oracle NCA and Web Protocols. Perform the desired actions and save the script.

#### 2. Define parameters for host and host arguments.

Define two variables, **serverHost** and **serverArgs**, for parameterization:

```
web_set_max_html_param_len("512");
web_reg_save_param("serverHost", "NOTFOUND=ERROR",
    "LB=<PARAM name=\"serverHost\" value=\"\", "RB=\">", LAST);
web_reg_save_param("serverArgs", "NOTFOUND=ERROR",
    "LB=<PARAM name=\"serverArgs\" value=\"\", "RB=\">", LAST);
```

#### 3. Assign values to **serverHost** and **serverArgs**:

```
web_url("step_name", "URL=http://server1.acme.com/test.htm", LAST);
```

4. **Modify the nca\_connect\_server statement from:**  
nca\_connect\_server("199.203.78.170", "9000"/\*version=107\*/,  
"module=e:\\appsnca...fnndnam=apps ");

to:

```
nca_connect_server("{ serverHost }", "9000"/*version=107*/, "{serverArgs}");
```

The script should now look like this:

```
web_set_max_html_param_len("512");
web_reg_save_param("serverHost", "NOTFOUND=ERROR",
    "LB=<PARAM name=\"serverHost\" value=\"", "RB=>", LAST);
web_reg_save_param("serverArgs", "NOTFOUND=ERROR",
    "LB=<PARAM name=\"serverArgs\" value=\"", "RB=>", LAST);
web_url("step_name", "URL=http://server1.acme/test.htm", LAST);
nca_connect_server("{serverHost}", "9000"/*version=107*/, "{serverArgs}");
```

## Correlate the icx\_ticket Variable

The **icx\_ticket** variable, is part of the information sent in the **web\_url** and **nca\_connect\_server** functions:

```
web_url("fnd_icx_launch.runforms",
"URL=http://ABC-123:8002/pls/VIS/fnd_icx_launch.runforms\?ICX_TICKET=5843A550589
47ED3=;RESP_APP=AR=;RESP_KEY=RECEIVABLES_MANAGER=;SECGRP_KEY=STANDARD", LAST);
```

This **icx\_ticket** value is different for each recording. It contains cookie information sent by the client. To correlate your recording, add **web\_reg\_save\_param** before the first occurrence of the recorded **icx\_ticket** value:

```
web_reg_save_param("icx_ticket", "LB=TICKET=", "RB==;RES", LAST);
...
web_url("fnd_icx_launch.runforms",
"URL=http://ABC-123:8002/pls/VIS/fnd_icx_launch.runforms\?ICX_TICKET={icx_ticket}=;RESP_APP=AR=;RESP_KEY=RECEIVABLES_MANAGER=;SECGRP_KEY=STANDARD", LAST);
```

**Note:** The left and right boundaries of **web\_reg\_save\_param** may differ depending on your application setup.

## Correlate the JServSessionIdroot Values

The **JServSessionIdroot** value is a cookie that the application sets to store the session ID. In most cases, VuGen automatically correlates this value and inserts a **web\_reg\_save\_param** function. If VuGen did not add this function automatically, you add it manually, replacing all of its occurrences with the parameter name.

To identify the value that you need to correlate, open the Execution log (**View > Output Window**) and locate the response body.

```
vuser_init.c(8): Set-Cookie: JServSessionIdroot=my1sanw2n1.JS4; path=/\r\n
vuser_init.c(8): Content-Length: 79\r\n
vuser_init.c(8): Content-Type: text/plain\r\n
```

```
vuser_init.c(8):      \r\n
vuser_init.c(8):      81-byte response body for "http://ABC-123/servlet/oracle fo
rms.servlet.ListenerServlet?ifcmd=getinfo=;
                           ifhost=mercury;ifip=123.45.789.12" (RelFrameId=1)
vuser_init.c(8):      /servlet/oracle.forms.servlet.ListenerServlet?JServSessionI
droot=my1sanw2n1.JS4\r\n
```

To correlate this dynamic value, insert a **web\_reg\_save\_param** function before the first occurrence and then replace the variable value with the parameter name throughout the script. In this example, the right and left boundaries are \r and \n, but you should check your specific environment to determine the exact boundaries in your environment.

```
web_reg_save_param("NCAJServSessionId","LB=\r\n\r\n","RB=\r","ORD=1",LAST);
web_url("f60servlet",
        "URL= http://ABC-123/servlet/oracle.forms.servlet.ListenerServlet?ifcmd=get
info=;" "ifhost=mercury;ifip=123.45.789.12", LAST);
web_url("oracle.forms.servlet.ListenerSer",
        "URL=http://ABC-123{NCAJServSessionId}?ifcmd=getinfo=;" "ifhost=mercury;ifi
p=123.45.789.12", LAST);
```

## How to Correlate Scripts - Microsoft .NET

This task describes how to correlate Microsoft .NET Vuser scripts.

### Correlate Scripts Using ADO.net Environments

#### 1. Locate the dataset in your script.

Display the Vuser script in the Editor and expand the applicable **DATASET\_XML** statement. Click **View > Snapshot**.

	CustomerID	CompanyName	ContactName	ContactTitle	Address
1	ABC	ABC Company	John Smith	Owner	One Way
2	ALFKI	Alfreds Futterkiste	Maria Anders	Sales Representative	Obere Str. 57
3	ANATR	Ana Trujillo Emparedados de la Casa Trujillo	Ana Trujillo	Owner	Avda. de la Constitución 2
4	ANTON	Antonio Moreno Taquería	Antonio Moreno	Owner	Mataderos 2
5	AROUT	Around the Horn	Thomas Hardy	Sales Representative	120 Hanover

#### 2. Locate the value.

Locate the value you want to correlate. To search for a value in a data grid, display the data grid in the Snapshot pane, and click **Search > Quick Find** to open the Search dialog box.

In the Search dialog box, click **Include in Search**, and then select the **Snapshots** check box.

#### 3. Create a correlation.

Right-click on the value in the grid that you want to correlate and select **Create Correlation**. The Create a correlation dialog box opens.

#### 4. Specify a parameter name.

Specify a parameter name, identical to the variable you defined earlier. Click **OK**. VuGen prompts you if you want to search for all occurrences. Click **OK**.

VuGen adds an **lr.save\_string** function before each dataset. For example:

```
lr.save_string("MyCustomerID", CustomerAndOrdersDataSet_3.Tables["Customers"]
    .Rows[0]["CompanyName"].ToString());
```

#### 5. Reference the parameter at a later point in the script.

Select the value you want to replace with a parameter and select **Replace with a parameter** from the right-click menu. Insert the saved variable name in the Parameter name box. Click OK. VuGen prompts you to replace all of the values with a parameter, using the **lr.eval\_string** function to evaluate the string's value.


```
lr.message("The customer ID is""+ lr.eval_string("{MyCustomerID}") + ");
```

Unlike other protocols, the script includes direct calls to the application or framework method. Therefore, you cannot replace the string value with the {paramName}—instead you must use **lr.eval\_string** to evaluate the parameter's value.

### Correlate with Output Parameters

For primitive values, you should generate the script with output parameter values and examine the output parameters for correlations.

1. Select **Recording > Recording Options**, and select the **General > Script** node.
2. Select the **Insert output parameter values** check box. Click **OK** to close the Recording Options dialog box.
3. Select **Record > Regenerate Script** to regenerate the script.
4. Search the commented output primitive values for correlations.



```
lr.log("Event 104: IEchoer_1.EchoInt16(short.MaxValue);");
Int16RetVal = IEchoer_1.EchoInt16(short.MaxValue);
// Int16RetVal = -32759;

Int16 arg_55;
arg_55 = short.MaxValue;
lr.log("Event 105: IEchoer_1.EchoInt16ByRef(ref arg_55);");
Int16RetVal = IEchoer_1.EchoInt16ByRef(ref arg_55);
// Int16RetVal = -32759;
// arg_55 = 32757;
```

For more information about using correlation functions, see the Function Reference (**Help > Function Reference**).

## How to Correlate Scripts - Java Scripts - Serialization

In RMI and some cases of CORBA, the client AUT creates a new instance of a Java object using the **java.io.Serializable** interface. It passes this instance as a parameter for a server invocation. In the following segment, the instance **p** is created and passed as a parameter.

```
// AUT code:  
java.awt.Point p = new java.awt.Point(3,7);  
map.set_point(p);  
:
```

The automatic correlation mechanism is ineffective here, since the object did not return from any previous call. In this case, VuGen activates the serialization mechanism and stores the object being passed as a parameter. It saves the information to a binary data file under the user folder. Additional parameters are saved as new binary data files, numbered sequentially. VuGen generates the following code:

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        java.awt.Point p = (java.awt.Point)lr.deserialize(0, false);  
        map.set_point(p);  
    }  
    :  
}
```

The integer passed to **lr.deserialize** represents the number of binary data files in the Vuser folder.

To parameterize the recorded value, use the public **setLocation** method (for information, see the JDK function reference). The following example uses the **setLocation** method to set the value of the object, **p**.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        java.awt.Point p = (java.awt.Point)lr.deserialize(0, false);  
        p.setLocation(2,9);  
        map.set_point(p);  
    }  
    :  
    :  
}
```

In certain instances the public method of **setLocation** is not applicable. As an alternative, you can use the API of your class that incorporate get or set accessor methods. If you are working with AUT classes that do not have get/set methods or use private methods, or if you are unfamiliar with the classes' API, you can use VuGen's built-in serialization mechanism. This mechanism allows you to expand objects in their ASCII representation and manually parameterize the script. You enable this mechanism in the Recording Options dialog box. For details, see "["Recording Properties > Serialization Options Node" on page 236](#)".

VuGen generates an **lr.deserialize** method that deserializes the data or displays complex data structures as serial strings. Once the structure is broken down to its components, it is easier to parameterize. The **lr.deserialize** method receives two arguments, a string and an integer. The string is the parameter's value that is to be substituted during replay. The integer is the index number of binary file to load.

If you choose not to expand objects in your script by clearing the Unfold Serialized Objects check box, you can control the serialization mechanism by passing arguments to the **lr.deserialize** method. The first argument is an integer indicating the number of binary files to load. The second integer is a boolean value:

<b>true</b>	Use VuGen's serialization mechanism.
<b>false</b>	Use the standard Java serialization mechanism.

The following segment shows a generated script in which the serialization mechanism was enabled.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        _string = "java.awt.Point __CURRENT_OBJECT = {" +  
            "int x = "#5#" +  
            "int y = "#8#" +  
        "}" ;  
        java.awt.Point p = (java.awt.Point)lr.deserialize(_string,0);  
        map.set_point(p);  
    }  
:  
}
```

The string values are placed between delimiters. The default delimiter is "#". You can change the delimiter in the **Serialization** tab of the recording options. Delimiters are used to speed up the parsing of the string during replay.

When modifying the string, you must maintain the following rules:

- Order of lines may not be changed. The parser reads the values one-by-one—not the member names.
- Only values between two delimiters may be modified.
- Object references may not be modified. Object references are indicated only to maintain internal consistency.
- **"\_NULL\_"** can appear as a value, representing the Java null constant. You can replace it with string type values only.
- Objects may be serialized anywhere in the script. For example, you can deserialize all objects

in the **init** method and use the values in the **action** method.

- Maintain internal consistency for the objects. For example, if a member of a vector is **elementCount** and you add an element, you must modify the element count.

In the following segment, a vector contains two elements:

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        _string = "java.util.Vector CURRENTOBJECT = {" +  
            "int capacityIncrement = #0#" +  
            "int elementCount = #2#" +  
            "java/lang/Object elementData[] = {" +  
                "elementData[0] = #First Element#" +  
                "elementData[1] = #Second Element#" +  
                "elementData[2] = _NULL_" +  
                ....  
                "elementData[9] = _NULL_" +  
            "}" +  
        "}" ;  
        _vector = (java.util.Vector)lr.deserialize(_string,0);  
        map.set_vector(_vector);  
    }  
:  
}
```

In the following example, one of the vector's elements was changed—a "\_NULL\_" value was changed to "Third element". In coordination with the addition of the new element, the **elementCount** member was modified to **3**.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        _string = "java.util.Vector CURRENTOBJECT = {" +  
            "int capacityIncrement = #0#" +  
            "int elementCount = #3# " +  
            "java/lang/Object elementData[] = {" +  
                "elementData[0] = #First Element#" +  
                "elementData[1] = #Second Element#" +  
                "elementData[2] = #Third Element#" +  
                ....  
                "elementData[9] = _NULL_" +  
            "}" +  
        "}" ;  
        _vector = (java.util.Vector)lr.deserialize(_string,0);  
        map.set_vector(_vector);  
    }  
:  
}
```

Due to the complexity of the serialization mechanism, which opens up the objects to ASCII representation, opening large objects while recording may increase the time required for script generation. To decrease this time, you can specify flags which will improve the performance of the serialization mechanism.

When adding **Ir.deserialize** to your script, we recommend that you add it to the **init** method—not the **action** method. This will improve performance since VuGen will only deserialize the strings once. If it appears in the **action** method, VuGen will deserialize strings for every iteration.

## How to Correlate Scripts - Java

VuGen's Java recorder attempts to automatically correlate statements in the generated script. It performs correlation on Java objects only. When it encounters a Java primitive (byte, character, boolean, integer, float, double, short, and long) during recording, the argument values appear in the script without association to variables. VuGen automatically correlates all objects, arrays of objects, and arrays of primitives. Note that Java arrays and strings are also considered objects.

VuGen employs several levels of correlation: Standard, Enhanced, Strings. You enable or disable correlation from the Recording options. An additional method of Serialization can be used to handle scripts where none of the former methods can be applied.

### Standard Correlation

Standard correlation refers to the automatic correlation performed during recording for simple objects, excluding object arrays, vectors, and container constructs.

When the recorded application invokes a method that returns an object, VuGen's correlation mechanism records these objects. When you run the script, VuGen compares the generated objects to the recorded objects. If the objects match, the same object is used. The following example shows two CORBA objects `my_bank` and `my_account`. The first object, `my_bank`, is invoked; the second object, `my_account`, is correlated and passed as a parameter in final line of the segment:

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        Bank my_bank = bankHelper.bind("bank", "shunra");  
        Account my_account = accountHelper.bind("account", "shunra");  
        my_bank.remove_account(my_account);  
    }  
:  
}
```

### Advanced Correlation

Advanced or **deep** correlation refers to the automatic correlation performed during recording for complex objects, such as object arrays and CORBA container constructs.

The deep correlation mechanism handles CORBA constructs (structures, unions, sequences, arrays, holders, `any's) as containers. This allows it to reference inner members of containers, additional objects, or different containers. Whenever an object is invoked or passed as a parameter, it is also compared against the inner members of the containers.

In the following example, VuGen performs deep correlation by referencing an element of an array. The remove\_account object receives an account object as a parameter. During recording, the correlation mechanism searches the returned array my\_accounts and determines that its sixth element should be passed as a parameter.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        my_banks[] = bankHelper.bind("banks", "shunra");  
        my_accounts[] = accountHelper.bind("accounts", "shunra");  
        my_banks[2].remove_account(my_accounts[6]);  
    }  
:  
}
```

The following segment further illustrates enhanced correlation. The script invokes the send\_letter object that received an address type argument. The correlation mechanism retrieves the inner member, address, in the sixth element of the my\_accounts array.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        my_banks = bankHelper.bind("bank", "shunra");  
        my_accounts = accountHelper.bind("account", "shunra");  
        my_banks[2].send_letter(my_accounts[6].address);  
    }  
:  
}
```

## String Correlation

String correlation refers to the representation of a recorded value as an actual string or a variable. When you disable string correlation (the default setting), the actual recorded value of the string is indicated explicitly within the script. When you enable string correlation, it creates a variable for each string, allowing you to use it at a later point in the script.

In the following segment, string correlation is enabled—you store the value returned from the get\_id method in a string type variable for use later on in the script.

```
public class Actions {  
    // Public function: init  
    public int init() throws Throwable {  
        my_bank = bankHelper.bind("bank", "shunra");  
        my_account1 = accountHelper.bind("account1", "shunra");  
        my_account2 = accountHelper.bind("account2", "shunra");  
        string = my_account1.get_id();  
        string2 = my_account2.get_id();  
        my_bank.transfer_money(string, string2);  
    }  
:  
}
```

# How to Correlate Scripts - XPath Correlation in Flex Vuser Scripts

This topic describes how to use XPath correlation in Flex Vuser scripts. You use the XML View inside the Snapshot pane to perform the correlation. Before you can successfully implement XPath correlation, you must first configure the recording options.

For details on how to use regular correlation in Flex Vuser scripts, see "[How to Correlate Scripts Using Design Studio](#)" on page 280.

1. **Configure the recording options.**
  - a. Select **Record > Recording Options**.
  - b. Under **Flex**, click **Externalizable Objects**.
  - c. Click **Serialize objects using**, and select **Custom Java Classes**.
  - d. Click the **Add jar or zip file** button .
  - e. On the LiveCycle installation discs, locate the following three files, and add them to the **Classpath Entries** list:
    - i. **flex.jar**
    - ii. **flex-messaging-common.jar**
    - iii. **flex-messaging-core.jar**

Ensure that the added files exist in the same location on all load generator machines.

2. Record the Vuser script.
3. In the Editor, click inside the **flex\_amf\_call** step that contains the data you want to correlate, or in the Step Navigator, double-click the **flex\_amf\_call** step that contains the data you want to correlate.
4. Click **View > Snapshot** or click the **Snapshot** button  on the VuGen toolbar.
5. In the Snapshot pane, click the **Response Body** tab.
6. On the right-side of the Snapshot pane, click the **XML View** tab.
7. In the XML View, locate and select the entire string that contains the dynamic data that requires correlation.
8. Right-click inside the selection, and select **Create Correlation**. The Design Studio opens. For details on how to use Design Studio, see "[Correlation Tab \[Design Studio\] Overview](#)" on page 275.

When the correlation is complete, VuGen adds a **web\_reg\_save\_parm\_xpath** step to the Vuser script.

## How to Correlate Scripts - COM Protocol

The following steps describe how to correlate COM Vuser scripts.

1. Select **View > Output** to display the output tabs at the bottom of the window. Check for errors in the Replay tab. Often, these errors can be corrected by correlation.
2. Select the relevant step in the Step Navigator, and view the step in the **Snapshot pane**.
3. Right click the value in the snapshot and select **Create correlation**. This will open the **Design Studio** window.
4. Select the value you would like to correlate by highlighting it in the grid and clicking the **Correlate** button.

When a value is correlated, VuGen adds the correlation parameter and saves the original value in a comment in the script.

```
252 | /* Correlation comment - Do not change! Original value='1' Name ='CorrelationParameter' Type ='Manual' */
253 | lrc_save_rs_param(_Recordset_45,
254 |     1,
255 |     2,
256 |     0,
257 |     "CorrelationParameter");
```

## How to Search for Values that Need Correlation

The following steps describe different ways to search for values that need correlation.

### Search by Comparing Scripts

1. Record a script and save it.
2. Create a new script and record the identical operations. Save the script.
3. Select **Tools > Compare with Vuser** to compare the scripts. For more details, see "[How to Compare Scripts Side by Side](#)" on page 91.
4. Differences in the script are highlighted. Review the differences to determine which ones may require correlation.

The screenshot shows the WDiff utility window with two tabs: C:\temp\s2\Action.c and C:\temp\s1\Action.c. Both tabs contain nearly identical script code, with minor differences highlighted in yellow. The code includes web\_submit\_data, lr\_think\_time, and web\_link functions.

```
web_submit_data("printpost.asp",
    "Action=http://testserver/myapplication",
    "Method=POST",
    "RecContentType=text/html",
    "Referer=http://testserver/myapplication",
    "Snapshot=t5.inf",
    "Mode=HTML",
    ITEMDATA,
    "Name=serial", "Value=123-456-9999", END
    "Name=ident", "Value=620916F9b8Fc68a5891
    LAST);
    lr_think_time(9);
    web_link(":123-456-9999:620916F9b8Fc68a5894cb22
    "Text=:123-456-9999:620916F9b8Fc68a5894
    "Snapshot=t6.inf",
    LAST);
```

```
web_submit_data("printpost.asp",
    "Action=http://testserver",
    "Method=POST",
    "RecContentType=text/html"
    "Referer=http://testserver",
    "Snapshot=t5.inf",
    "Mode=HTML",
    ITEMDATA,
    "Name=serial", "Value=123-
    "Name=ident", "Value=c398-
    LAST);
    lr_think_time(9);
    web_link(":123-456-9999:c3981fa8d
    "Text=:123-456-9999:c3981
    "Snapshot=t6.inf",
    LAST);
```

**Note:** *WDiff* is the default utility, but you can specify a custom comparison tool. For more information, see ["How to Compare Scripts Side by Side" on page 91](#).

## Replay Log Search

1. Scan the script in script view for strings that may need correlation such as hash strings, random strings, session ID's, and so on.
2. Search the generation log for the first time that the string appears (this is the response from the server).
3. Search the extended replay log for the same response. Check to see if this response contains a different string within the same boundaries as the original suspected string. If yes, this string requires correlation.

## How to Modify Correlation Definitions

You can modify correlation definitions to help eliminate dynamic values that do not require correlation. These tasks describe how to modify boundary based, regular expression, and XPath query correlation definitions for record or response correlation.

### Modifying Boundary Based Correlation Definitions

1. Click the **Design Studio** button on the VuGen toolbar.
2. Select a dynamic value from the correlation grid and expand **Details**.
3. Edit the **Left Boundary** or **Right Boundary** under the **Correlation Definition** section. You can modify the definition by adding or deleting text.



4. Click **Apply this Definition**.

The **Apply this Definition** button will not be enabled unless the modified boundary definition occurs in the snapshot and the script.

**Note:** If you do not apply the definition before selecting another dynamic value in the grid, your changes will be lost. If you select **Replay & Scan** before correlating your value with the modified definition, your changes will be lost.

## Modifying Regular Expression Correlation Definitions

1. Click the  **Design Studio** button on the VuGen toolbar.
2. Select a dynamic value from the correlation grid and expand **Details**.
3. Edit the **Regular Expression** under the **Correlation Definition** section.
4. Click **Apply this Definition**.

The **Apply this Definition** button will not be enabled unless the modified boundary definition occurs in the snapshot and the script.

**Note:** If you do not apply the definition before selecting another dynamic value in the grid, your changes will be lost. If you select **Replay & Scan** before correlating your value with the modified definition, your changes will be lost.

## Modifying XPath Correlation Definitions

1. Click the  **Design Studio** button on the VuGen toolbar.
2. Select a dynamic value from the correlation grid and expand **Details**.
3. Edit the XPath definition under the **Correlation Definition** section.
4. Click **Apply this Definition**.

The **Apply this Definition** button will not be enabled unless the modified boundary definition occurs in the snapshot and the script.


**Note:** If you do not apply the definition before selecting another dynamic value in the grid, your changes will be lost. If you select **Replay & Scan** before correlating your value with the modified definition, your changes will be lost.

## Modifying Winsocket Correlation Definitions

1. Winsocket dynamic values are correlated from the snapshot. To access, select the relevant step in the **Step Navigator**, and view the step in the **Snapshot pane**. The Winsocket protocol has both a hex and text snapshot.

Right click the value in the snapshot and select **Create correlation** or **Create boundary correlation**. This will open the  **Design Studio** window.

2. Select a dynamic value from the correlation grid and expand **Details**.
3. If you selected **Create correlation**, edit the Data Range in the **Correlation Definition** section. If you selected **Create boundary correlation**, edit the left or right boundary.



4. Click **Apply this Definition**.


The **Apply this Definition** button will not be enabled unless the modified boundary definition occurs in the snapshot.

View the following images that display both a Data Range definition and a Boundary definition.


## LoadRunner User Guide

### Script Workflow

Data Range definition correctly modified



Boundary base definition correctly modified



**Note:** If you do not apply the definition before selecting another dynamic value in the grid, your changes will be lost. If you select **Replay & Scan** before correlating your value with the modified definition, your changes will be lost.

**Note:** Correlation Rule definitions cannot be modified using this method.

## How to Exclude Content Based on Content-Type

The HTTP header "content-type:" defines the type of HTTP response(content). This topic describes how to exclude content by content-type from the correlation scan by modifying the IgnoredContent.xml file.

1. Open the <LoadRunner Installation folder>\config\IgnoredContent.xml in a text editor.

### IgnoredContent.xml

```
<?xml version="1.0" encoding="utf-8" ?>
<IgnoredHttpContentTypes xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xmlns:xsd="http://www.w3.org/2001/XMLSchema">
  <CONTENT_TYPES>
    <string>application/(?!x-amf|json))</string>
    <string>audio/</string>
    <string>image/</string>
    <string>model/</string>
    <string>video/</string>
  </CONTENT_TYPES>
</IgnoredHttpContentTypes>
```

2. Modify the IgnoredContent.xml to exclude content-type by inserting a string or regular expression.

If you enter:	Correlation studio will:
image/	Ignore any content type beginning with image/ such as image/gif, image/jpeg, image/png
application/(!(json x-amf))	Ignore content type that begins with application/ except for content type application/json or application/x-amf.

### Example of content added to the IgnoredContent.xml

In our example, the correlation engine will ignore application content except for x-amf , json, or javascript application content.

```
<?xml version="1.0" encoding="utf-8" ?>
<IgnoredHttpContentTypes xmlns:xsi="http://www.w3.org/2001/XMLSchema-
```


```
instance" xmlns:xsd="http://www.w3.org/2001/XMLSchema">
  <CONTENT_TYPES>
    <string>application/(?!x-amf|json|javascript))</string>
    <string>audio/</string>
    <string>image/</string>
    <string>model/</string>
    <string>video/</string>
  </CONTENT_TYPES>
</IgnoredHttpContentTypes>
```

## How to Exclude Strings from the Correlation Scan


This topic describes how to exclude strings from the correlation scan.

By default, the correlation engine will scan all plain and html text searching for correlations. Some of the candidates found may not be real correlations. To enhance correlation accuracy, you can configure VuGen to ignore certain items, either text strings or regular expressions by adding them to the **Excluded String List**.

### 1. Add a text string

- a. Select **Record > Recording Options > Correlations > Configuration**.
- b. Click the  button.
- c. Click the  button to open the **Excluded String List** dialog box.
- d. Enter the string and click **OK**.

### 2. Add a regular expression

- a. Select **Record > Recording Options > Correlations > Configuration**.
- b. Click the  button.
- c. Click the  button to open the **Excluded String List** dialog box.
- d. Enter a regular expression and check the **Regular Expression** box or

Select the  button to view and select from a list box of regular expression character classes and complete the regular expression.

**For example:**

If you enter:	Correlation studio will:
getCachedId	Exclude getCachedID as a correlation candidate.
^navurl:.*	Exclude strings such as navurl:\\any_char, navurl:1234 as correlation candidates.

d. Click **OK**.

### 3. Delete an excluded string

- a. Highlight the string in the **Excluded String List** dialog box.
- b. Click the  button.

## Correlation Functions - Database Vuser Scripts

When working with Database Vuser scripts, (DbLib, CtLib, Oracle, and so forth) you can use VuGen's automated correlation feature to insert the appropriate functions into your script. The correlating functions are:

- **Ird\_save\_col** saves a query result appearing in a grid, to a parameter. This function is placed before fetching the data. It assigns the value retrieved by the subsequent **Ird\_fetch** to the specified parameter.  
(**Ird\_ora8\_save\_col** for Oracle 8 and higher)
- **Ird\_save\_value** saves the current value of a placeholder descriptor to a parameter. It is used with database functions that set output placeholders (such as certain stored procedures under Oracle).
- **Ird\_save\_ret\_param** saves a stored procedure's return value to a parameter. It is used primarily with database procedures stored in DbLib that generate return values.

**Note:** VuGen does not apply correlation if the saved value is invalid or NULL (no rows returned).

For more information about these functions and their arguments, see the Function Reference ([Help > Function Reference](#)).

## Correlation Functions - Java Vuser Scripts

To correlate statements for Java Vusers, you can use the Java Vuser correlation functions. These functions may be used for all Java type Vusers, to save a string to a parameter and retrieve it when required.

<b>lr.eval_string</b>	Replaces a parameter with its current value.
<b>lr.eval_data</b>	Replaces a parameter with a byte value.
<b>lr.eval_int</b>	Replaces a parameter with an integer value.
<b>lr.eval_string</b>	Replaces a parameter with a string.
<b>lr.save_data</b>	Saves a byte as a parameter.
<b>lr.save_int</b>	Saves an integer as a parameter.
<b>lr.save_string</b>	Saves a null-terminated string to a parameter.

When recording a CORBA or RMI session, VuGen performs correlation internally. For more information, see ["How to Correlate Scripts - Java" on page 299](#).

## Using the Java String Functions

When programming Java Vuser scripts, you can use the Java Vuser string functions to correlate your scripts. In the following example, **lr.eval\_int** substitutes the variable **ID\_num** with its value, defined at an earlier point in the script.

```
lr.message(" Track Stock: " + lr.eval_int(ID_num));
```

In the following example, **lr.save\_string** assigns John Doe to the parameter Student. This parameter is then used in an output message.

```
lr.save_string("John Doe", "Student");
// ...
lr.message("Get report card for " + lr.eval_string("<Student>"));
classroom.getReportCard
```

## Web\_reg\_save\_param function details

When you run a script, the **web\_reg\_save\_param** function scans the subsequent HTML page that is accessed. You specify a left and/or right boundary and VuGen searches for text between those boundaries. When VuGen finds the text, it assigns it to a parameter.

The function's syntax is as follows:

```
int web_reg_save_param (const char *mpszParamName, <List of Attributes>, LAST);
```

The following table lists the available attributes. Note that the attribute value strings (for example, Search=all) are not case sensitive.

<b>NotFound</b>	The handling method when a boundary is not found and an empty string is generated. "ERROR," the default, indicates that VuGen should issue an error when a boundary is not found. When set to "EMPTY," no error message is issued and script execution continues. Note that if Continue on Error is enabled for the script, then even when NOTFOUND is set to "ERROR," the script continues when the boundary is not found, but it writes an error message to the Extended log file.
<b>LB</b>	The left boundary of the parameter or the dynamic data. This parameter must be a non-empty, null-terminated character string. Boundary parameters are case sensitive; to ignore the case, add "/IC" after the boundary. Specify "/BIN" after the boundary to specify binary data.
<b>RB</b>	The right boundary of the parameter or the dynamic data. This parameter must be a non-empty, null-terminated character string. Boundary parameters are case sensitive; to ignore the case, add "/IC" after the boundary. Specify "/BIN" after the boundary to specify binary data.
<b>RelFrameID</b>	The hierarchy level of the HTML page relative to the requested URL. The possible values are ALL or a number.
<b>Search</b>	The scope of the search—where to search for the delimited data. The possible values are Headers (search only the headers), Body (search only body data, not headers), or ALL (search body and headers). The default value is ALL.
<b>ORD</b>	This optional parameter indicates the ordinal or occurrence number of the match. The default ordinal is 1. If you specify "All," it saves the parameter values in an array.
<b>SaveOffset</b>	The offset of a sub-string of the found value, to save to the parameter. The default is 0. The offset value must be non-negative.
<b>Savelen</b>	The length of a sub-string of the found value, from the specified offset, to save to the parameter. The default is -1, indicating until the end of the string.
<b>Convert</b>	The conversion method to apply to the data: HTML_TO_URL: convert HTML-encoded data to a URL-encoded data format HTML_TO_TEXT: convert HTML-encoded data to plain text format

## Correlation Functions - C Vuser Scripts

To correlate statements for protocols that do not have specific functions, you can use the C Vuser correlation functions. These functions can be used for all C-type Vusers, to save a string to a parameter and retrieve it when required.

<b>lr_eval_string</b>	Replaces all occurrences of a parameter with its current value.
<b>lr_save_string</b>	Saves a null-terminated string to a parameter.
<b>lr_save_var</b>	Saves a variable length string to a parameter.

For additional information about the syntax of these functions, see the Function Reference ([Help > Function Reference](#)).

## Using lr\_eval\_string

In the following example, lr\_eval\_string replaces the parameter row\_cnt with its current value. This value is sent to the Output window using lr\_output\_message.

```
lrd_stmt(Csr1, "select count(*) from employee", -1, 1 /*Deferred*/, ...);
lrd_bind_col(Csr1, 1, =;COUNT_D1, 0, 0);
lrd_exec(Csr1, 0, 0, 0, 0, 0);
lrd_save_col(Csr1, 1, 1, 0, "row_cnt");
lrd_fetch(Csr1, 1, 1, 0, PrintRow2, 0);
lr_output_message("value: %s", lr_eval_string("The row count is: <row_cnt>"));
```

## Using lr\_save\_string

To save a NULL terminated string to a parameter, use **lr\_save\_string**. To save a variable length string, use **lr\_save\_var** and specify the length of the string to save.

In the following example, lr\_save\_string assigns 777 to a parameter emp\_id. This parameter is then used in another query or for further processing.

```
lrd_stmt(Csr1, "select id from employees where name='John'",...);
lrd_bind_col(Csr1,1,=;ID_D1,...);
lrd_exec(Csr1, ...);
lrd_fetch(Csr1, 1, ...);
/* GRID showing returned value "777" */
lr_save_string("777", "emp_id");
```

## Design Studio [Correlation Tab] Dialog Box

This dialog box enables you to scan for, correlate, and view information about dynamic values in your script.

<b>To access</b>	Click the  <b>Design Studio</b> button on the VuGen toolbar. The button is enabled only when you have a recorded script in the Solution Explorer.
<b>Important information</b>	<a href="#">"Correlation Tab [Design Studio] Overview" on page 275</a>
<b>Relevant tasks</b>	<a href="#">"How to Correlate Scripts Using Design Studio" on page 280</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Correlation Tab</b>	
<b>Replay and Scan</b>	Design studio scans for dynamic values using all enabled types: rule, record, and replay.

UI Element	Description
<b>Correlate</b>	Replace a dynamic value in the script with a correlation parameter.
<b>Add as Rule</b>	<p>Add dynamic value definition as a rule.</p> <p><b>Rule name.</b> Enables you to specify a rule name.</p> <p><b>Application Name.</b> Enables you to associate the rule to a specific application.</p> <p>For details, see "<a href="#">Correlations &gt; Rules</a>" on page 186.</p>
<b>Undo Correlation</b>	Replace the correlation parameter with the original dynamic value.
<b>Discard</b>	<p>Delete the selected dynamic values from the correlation grid. You can only use the discard action when the dynamic value has a status of <b>New</b>.</p> <p>In addition, this action adds the text to the list of excluded strings. You can edit the list in <b>Recording Options &gt; Correlation &gt; Configuration &gt; Excluded string list</b>.</p>
<b>View</b>	<p>Enables you to filter values found for correlation by the following types:</p> <ul style="list-style-type: none"> <li>• All</li> <li>• New</li> <li>• Correlated</li> </ul>
<b>Correlation Grid</b>	
Displays details about each dynamic value in the script	
<b>Type</b>	<p>Displays which engine found the dynamic value for correlations:</p> <ul style="list-style-type: none"> <li>• Record</li> <li>• Rules</li> <li>• Replay</li> <li>• Manual</li> </ul>

UI Element	Description
<b>Found/Replace</b>	<p>Displays information about the number of dynamic values found with the same definitions. Since you can perform partial correlation, meaning you can replace specific occurrences, the information displayed depends on if you have correlated the value or not.</p> <ul style="list-style-type: none"> <li><b>Before you correlate</b> Number of values that can be replaced/ Number of values found</li> <li><b>After you correlate</b> Number of values that have been replaced/Number of values found.</li> </ul>
<b>Status</b>	Displays correlation status of the dynamic value from the script:
	<ul style="list-style-type: none"> <li>New</li> <li>Correlated</li> </ul>
<b>Text in Response</b>	Displays the string of the dynamic value from the script.
<b>Correlation Parameter</b>	Displays the correlation parameter name of the dynamic value.
<b>Correlation Details Chevron</b>	
Displays details about the dynamic value in the snapshot/script	
<b>Original Snapshot Step Tab</b>	
<b>Step in Script Details</b>	
<b>Name</b>	Displays the step name in the script where the dynamic value was found.
<b>Line</b>	Displays the line of the script where the dynamic value was found.
<b>Action Name</b>	Displays the name of action from the script where the dynamic value was found.
<b>Description</b>	Displays a description of the step.
<b>Correlation Definition Details</b>	
<b>Type</b>	<p>Display API function that will be used to correlate the value.</p> <p>Regular expression: web_reg_save_param_regexp</p> <p>Boundary based: web_reg_save_param_ex</p>

UI Element	Description
<b>Definition</b>	<p>Displays the definition of the dynamic value.</p> <ul style="list-style-type: none"> <li><b>Regular Expression.</b> Dynamic value correlation is defined by a regular expression. A regular expression is a special text string for describing a search pattern.</li> <li><b>Boundary based.</b> Dynamic value correlation is defined by left and right boundary text strings.</li> </ul>
<b>Apply Definition</b>	<p>Enables you to select which definition to apply to the dynamic value. You can scroll through the definition of the dynamic value in <b>Occurrences in Snapshot</b> by clicking <b>Prev</b> or <b>Next</b> buttons.</p>
<b>Occurrences in Snapshot</b>	<p><b>Record snapshot.</b> Displays all the occurrences of the dynamic value in the record snapshot once the script has been replayed. You can scroll to view each occurrence in the snapshot.</p>  <p><b>Replay snapshot.</b> If the scan type of <b>Replay</b> has been selected, <b>Design Studio</b> displays all the occurrences of the dynamic value in the replay snapshot once the script has been replayed. You can scroll to view each occurrence in the snapshot.</p> <p><b>Note:</b> Once the value has been correlated, the replay snapshot will be blank. If you modify the <b>Correlation Definition</b>, the replay snapshot will be blank.</p>
<b>Correlation Occurrences Tab</b>	
<b>Occurrences in Script</b>	<p>Displays the occurrences of the dynamic value in your script. You can correlate all the values or select individual values to correlate by selecting the check box adjacent to the occurrence.</p>
<b>Options</b>	<p>Opens the <b>Recording Options</b> dialog box.</p> <p>For details, see:</p> <p><a href="#">"Correlations &gt; Configuration" on page 184</a></p> <p><a href="#">"Correlations &gt; Rules" on page 186</a></p>

# Replaying a Vuser Script

The **Replaying a Vuser Script** section describes the various methods that are available to replay Vuser scripts.

## Replaying - Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the fourth step, replaying a Vuser script.



After recording a Vuser script, you use VuGen to replay the script. This helps to test the basic functionality of the Vuser script, as well as helps you to uncover errors and issues that need to be addressed. The need for correlation is a typical issue that is revealed when you first replay a script. For details on correlation, see ["Correlation Overview" on page 274](#). When the replay is successful, you are ready to add load-testing functionality to the script. Such functionality could include parameterization, transactions, and rendezvous points.

- For details on how to replay a Vuser script, see ["How to Replay a Vuser Script" below](#).
- If you encounter problems when you replay the script, you can use VuGen's debugging functionality to help resolve the issues. For details, see ["Debugging - Overview" on page 388](#).
- For details on the files that VuGen creates during a script replay, see ["Files Generated During Replay" on page 386](#).
- You can use bookmarks to navigate between sections of the script. For details, see ["Bookmarks Overview" on page 382](#).
- You can run a Vuser script from a Windows command prompt. For details, see ["How to Run a Vuser Script from a Command Prompt" on page 382](#).
- You can run a Vuser script from a Linux command line. For details, see ["How to Run a Vuser Script from a Linux Command Line" on page 383](#).

## How to Replay a Vuser Script

This task describes how to replay a Vuser script.

### 1. Configure the run-time settings and replay options

- a. Run-time settings control how your Vuser script is replayed. Access the desired run-time settings by double-clicking the **Run-Time Settings** node in the **Solution Explorer**.

For an overview of run-time settings, see Run-Time Settings Overview.

- b. Specify replay options by selecting **Tools > Options**. For details on options, see "[Options Overview](#)" on page 94.

## 2. Replay the script

To run a Vuser script until the end of the script or until the next breakpoint, perform one of the following:

- Select **Replay > Run**.
- Click the **Run** button  on the Vuser toolbar.
- Press **F5**.

**Note:** The status of the Vuser script execution appears in the lower left corner of VuGen. The script execution status may be **Ready**, **Running**, or **Paused**.

- To stop a script that is running, click the **Stop Replay**  button on the VuGen toolbar.
- To pause a script that is running, click the **Pause**  button on the VuGen toolbar.
- To continue running a script that is paused, click the **Continue**  button on the VuGen toolbar.

## 3. View the logs for detailed information

You can view detailed information about how your script behaved during the replay. This information appears in the Output window. For details, see "[Output Pane](#)" on page 124.

To learn more about replaying a Vuser script, see "[Replaying - Overview](#)" on the previous page.

# Run-Time Settings

This section describes the various Vuser run-time settings.

## **Run-Time Settings - Miscellaneous Topics**

This section contains a variety of topics relating to run-time settings.

### **Content Checking Overview**

You use the ContentCheck run-time options to check the contents of a page for a specific string. This is useful for detecting non-standard errors. In normal operations, when your application server fails, the browser displays a generic HTTP error page indicating the nature of the error. The standard error pages are recognized by VuGen and treated as errors, causing the script to fail. Some application servers, however, issue their own error pages that are not detected by VuGen as

error pages. The page is sent by the server and it contains a formatted text string, stating that an error occurred.

For example, suppose that your application issues a custom page when an error occurs, containing the text **ASP Error**. You instruct VuGen to look for this text on all returned pages. When VuGen detects this string, it fails the replay.

**Note:** VuGen searches the body of the pages—not the headers.

## ***Copying, Importing, and Exporting Run-Time Settings***

This topic describes how to copy, import, and export run-time settings from one Vuser script to another. This functionality is available for all Vuser protocols. For an overview of the run-time settings functionality, see Run-Time Settings - Overview.

**Note:** In all the tasks below:

- The script from which the run-time settings are being taken will be referred to as Script A
- The receiving script will be referred to as Script B.

### **How to copy run-time settings from one script to another**

1. Make sure that both Script A and Script B are open.
2. In the Solution Explorer pane, right click on the Run-Time Settings node of Script A and select **Copy** in the context menu.
3. In the Solution Explorer pane, right click on the Run-Time Settings node of Script B and select **Paste** in the context menu.
4. In the message box asking if you are sure, click **Yes**.
5. Save Script B.

**Note:** The settings from Script A are copied to Script B using the following logic:

- Setting in Script A and setting in Script B: The setting in Script B is overwritten
- Setting in Script A and no setting in Script B: The setting in Script B is set to the value of the setting in Script A.
- No setting in Script A and setting in Script B: The setting in Script B remains the same.

## How to export run-time settings from Script A

1. Open Script A.
2. In the Solution Explorer pane, right click on the Run-Time Settings node of the script and select **Export**.
3. In the Export run-time settings dialog, choose a location for the file, type a name for the file, ensure that the file type is Script Settings Files (\*.xsss) and click **OK**.

## How to import run-time settings to Script B

1. Open Script B.
2. In the Solution Explorer pane, right click the Run-Time Settings node of on the script and select **Import**.
3. In the Import run-time settings dialog, select the file to be imported and click **OK**.
4. In the message box asking if you are sure, click **Yes**.
5. Save Script B.

**Note:** The settings from Script A are copied to Script B using the following logic:

- Setting in Script A and setting in Script B: The setting in Script B is overwritten
- Setting in Script A and no setting in Script B: The setting in Script B is set to the value of the setting in Script A.
- No setting in Script A and setting in Script B: The setting in Script B remains the same.

## How to revert run-time settings in a script node to the default settings

1. In the Solution Explorer pane, select the Run-Time Settings node of the script to be changed and navigate to the required setting.
2. Click **Use Defaults**.
3. Click **OK**.
4. Save the script. Only the defaults for the displayed node are changed. If you want to revert to the default settings for all the run-time settings, you must do so for each individual node separately.

**Note:**

- Run-time settings can only be modified with Copy/Paste and Import/Export from within VuGen.
- Copy/Paste is only effective for the common run-time settings such as Think Time, Iterations, and Log.

## Multithreading

The Controller uses a driver program (such as *mdrv.exe* or *r3vuser.exe*) to run your Vusers. If you run each Vuser as a process, then the same driver program is launched (and loaded) into the memory again and again for every instance of the Vuser. Loading the same driver program into memory uses up large amounts of RAM (random access memory) and other system resources. This limits the numbers of Vusers that can be run on any load generator.

Alternatively, if you run each Vuser as a thread, the Controller launches only one instance of the driver program (such as *mdrv.exe*), for every 50 Vusers (by default). This driver process/program launches several Vusers, each Vuser running as a thread. These threaded Vusers share segments of the memory of the parent driver process. This eliminates the need for multiple re-loading of the driver program/process saves much memory space, thereby enabling more Vusers to be run on a single load generator.

To configure these options, see "[General > Miscellaneous Node](#)" on page 348.

## Protocol Compatibility Table

The following table lists the Vuser protocols and which run-time setting nodes are available for each protocol.

Protocol	Run-Time Setting Nodes
.NET	<ul style="list-style-type: none"><li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li><li>• .NET - .NET Environment</li></ul>
Ajax	<ul style="list-style-type: none"><li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li><li>• Network - Speed Simulation</li><li>• Browser - Browser Emulation</li><li>• Internet Protocol - Proxy, Preferences, Download Filters, ContentCheck</li></ul>
C Vuser	<ul style="list-style-type: none"><li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li></ul>

Protocol	Run-Time Setting Nodes
<b>Citrix ICA</b>	<ul style="list-style-type: none"> <li>• General – Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network – Speed Simulation</li> <li>• Citrix – Configuration, Synchronization</li> </ul>
<b>COM/DCOM</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> </ul>
<b>DNS</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> </ul>
<b>FTP</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> </ul>
<b>Flex</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Flex - RTMP, Configuration, Externalizable Objects</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, Content Check</li> </ul>
<b>IMAP (Internet Messaging)</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> </ul>
<b>Java over HTTP</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Java Environment Settings - Classpath, Java VM</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters</li> </ul>
<b>Java Record Replay, Java Vuser</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Java Environment Settings - Classpath, Java VM</li> </ul>

Protocol	Run-Time Setting Nodes
<b>LDAP</b>	<ul style="list-style-type: none"> <li>General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>Network - Speed Simulation</li> </ul>
<b>MMS (Media Player)</b>	<ul style="list-style-type: none"> <li>General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>Network - Speed Simulation</li> </ul>
<b>RDP</b>	<ul style="list-style-type: none"> <li>General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>Network - Speed Simulation</li> <li>RDP - Configuration, Synchronization, Advanced, RDP Agent</li> </ul>
<b>MAPI (Microsoft Exchange )</b>	<ul style="list-style-type: none"> <li>General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> </ul>
<b>MMS (Multimedia Messaging Service)</b>	<ul style="list-style-type: none"> <li>General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>Browser - Browser Emulation</li> <li>MMS - Server and Protocol</li> <li>WAP - Radius, Gateway</li> <li>Internet Protocol - Proxy, Preferences, Download Filters</li> </ul>
<b>ODBC</b>	<ul style="list-style-type: none"> <li>General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> </ul>
<b>Oracle 2-Tier</b>	<ul style="list-style-type: none"> <li>General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> </ul>
<b>Oracle NCA</b>	<ul style="list-style-type: none"> <li>General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>Network - Speed Simulation</li> <li>Oracle NCA - Client Emulation</li> </ul>

Protocol	Run-Time Setting Nodes
<b>Oracle Web Applications 11i</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, ContentCheck</li> <li>• Oracle NCA - Client Emulation</li> </ul>
<b>POP3</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> </ul>
<b>RTE</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• RTE - RTE</li> </ul>
<b>SAP Web</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, ContentCheck</li> </ul>
<b>SAP Click &amp; Script</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, ContentCheck</li> </ul>
<b>SAP GUI</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• SAP GUI - General</li> <li>• Network - Speed Simulation</li> </ul>

Protocol	Run-Time Setting Nodes
<b>Siebel Web</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, ContentCheck</li> </ul>
<b>Silverlight</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Silverlight - Services</li> <li>• Data Format Extensions - Configuration</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, ContentCheck</li> </ul>
<b>SMTP</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> </ul>
<b>TruClient Ajax</b>	<ul style="list-style-type: none"> <li>• General - Pacing, Additional Attributes, Log, Load Mode, Browser Settings, Other Settings</li> </ul>
<b>Web (HTTP/HTML)</b>	<ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• Network - Speed Simulation</li> <li>• Browser - Browser Emulation</li> <li>• Internet Protocol - Proxy, Preferences, Download Filters, Content Check</li> <li>• Data Format Extension - Configuration</li> </ul>

Protocol	Run-Time Setting Nodes
<b>Web Services</b>	<ul style="list-style-type: none"><li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li><li>• Network - Speed Simulation</li><li>• JMS - Advanced</li></ul>
<b>Windows Sockets</b>	<ul style="list-style-type: none"><li>• General - Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li><li>• Network - Speed Simulation</li></ul>

## ***Browser > Browser Emulation Node***

Enables you to configure the browser related run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Browser &gt; Browser Emulation</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Simulate Browser Cache</b>	<p>Instructs the Vuser to simulate a browser with a cache (enabled by default). Even if you disable this option, each resource is only downloaded once for each page, even if it appears multiple times. A resource can be an image, a frame, or another type of script file. Enabling this options allows you to set the following options:</p> <ul style="list-style-type: none"> <li>• <b>Cache URLs requiring content (HTML).</b> Instructs VuGen to cache only the URLs that require the HTML content. The content may be necessary for parsing, verification, or correlation. When you select this option, HTML content is automatically cached.</li> <li>• <b>Specify URLs requiring content in addition to HTML pages.</b> Allows you to specify addiitonal (non- html) content types that you want to store in the cache. Separate all contents types with a semicolon in the following row, <b>Content types</b>.</li> </ul> <p><b>Tip:</b> To maintain a smaller memory footprint for the virtual users, keep this option disabled unless it is an explicit requirement for your test.</p> <ul style="list-style-type: none"> <li>• <b>Check for newer versions of stored pages every visit to the page.</b> Instructs the browser to check for later versions of the specified URL than those stored in the cache. When you enable this option, VuGen adds the "If-modified-since" attribute to the HTTP header. This option brings up the most recent version of the page, but also generates more traffic during the scenario or session execution.</li> </ul> <p><b>Default value:</b> disabled.</p>
<b>Download non-HTML resources</b>	<p>Instructs Vusers to load graphic images when accessing a Web page during replay. This includes both graphic images that were recorded with the page, and those which were not explicitly recorded along with the page. When real users access a Web page, they wait for the images to load. Therefore, enable this option if you are trying to test the entire system, including end-user time. To increase performance and not emulate real users, disable this option.</p> <p>Disable this option if you experience discrepancies in image checks, since some images vary each time you access a Web page (for example, advertiser banners).</p>

UI Element	Description
<b>Simulate a new user each iteration</b>	<p>Instructs VuGen to reset all HTTP contexts between iterations to their states at the end of the init section. This setting allows the Vuser to more accurately emulate a new user beginning a browsing session. It deletes all cookies, closes all TCP connections (including keep-alive), clears the emulated browser's cache, resets the HTML frame hierarchy (frame numbering will begin from 1) and clears the user-names and passwords. (Enabled by default)</p> <p><b>Note:</b> Async conversations are terminated at the end of each iteration even if this setting is disabled.</p> <ul style="list-style-type: none"> <li>• <b>Clear cache on each iteration.</b> Clears the browser cache for each iteration in order to simulate a user visiting a Web page for the first time. Clear the check box to disable this option and allow Vusers to use the information stored in the browser's cache, simulating a user who recently visited the page.</li> </ul>
<b>User Agent-Selection</b>	<p>Allows you to select the browser to emulate or specify a custom user-agent string. All Internet Vuser headers include a User Agent header that identifies the type of browser (or toolkit for Wireless) that is being emulated. For example, <b>Mozilla/4.0 (compatible; MSIE 6.0; Windows; Trident/4.0; English (United States))</b> identifies the browser as Internet Explorer running under Windows on an Intel machine.</p> <p><b>Use browser.</b> Uses a standard browser available from the drop-down list. You select the version, platform and language.</p> <p><b>Custom browser.</b> Indicates a custom user-agent string.</p>

## Citrix > Configuration Node

Enables you to set the Citrix configuration run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Citrix &gt; Configuration</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Queue mouse movements and keystrokes</b>	<p>Instructs Vusers to create a queue of mouse movements and keystrokes, and send them as packets to the server less frequently. This setting reduces network traffic with slow connections. Enabling this option makes the session less responsive to keyboard and mouse movements.</p> <p><b>Default value:</b> disabled.</p>

<b>Sound quality</b>	Specifies the quality of the sound. If the client machine does not have a 16-bit Sound Blaster-compatible sound card, select <b>Sound Off</b> . With sound support enabled, you will be able to play sound files from published applications on your client machine.
<b>SpeedScreen Latency Reduction</b>	The mechanism used to enhance user interaction when the network speed is slow. You can turn this mechanism <b>on</b> or <b>off</b> , depending on the network speed. The <b>auto</b> option turns it on or off based on the current network speed. If you do not know the network speed, set this option to <b>Use Server Default</b> to use the machine's default.
<b>Use data compression</b>	Instructs Vusers to compress the transferred data. You should enable data compression if you have a limited bandwidth. <b>Default value:</b> enabled.
<b>Use disk cache for bitmaps</b>	Instructs Vusers to use a local cache to store bitmaps and commonly-used graphical objects. You should enable this option if you have a limited bandwidth. <b>Default value:</b> disabled.

## Citrix > Synchronization Node

Enables you to set the Citrix synchronization run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Citrix &gt; Synchronization</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Default Image Sync Tolerance</b>	This setting controls the level of equality two images must share to be considered synchronized. <b>Exact.</b> Must have a 100% match. <b>Low.</b> Must have a 95% match. <b>Medium.</b> Must have an 85% match. <b>High.</b> Must have a 70% match. <b>Default value:</b> Exact.
<b>Timeout</b>	<ul style="list-style-type: none"> <li><b>Connect Time.</b> The time (in seconds) to wait idly at an established connection before exiting.</li> <li><b>Waiting Time.</b> The time (in seconds) to wait idly at a synchronization point before exiting.</li> </ul>
<b>Typing rate</b>	The delay (in milliseconds) between keystrokes.

UI Element	Description
<b>Default Image Sync Tolerance</b>	The default tolerance level for performing synchronization on images: <b>Exact</b> , <b>Low</b> , <b>Medium</b> , or <b>High</b> .
<b>Mouse click internal delay</b>	The delay (in milliseconds) between sending MOUSE_UP and MOUSE_DOWN events.
<b>Bitmap polling delay</b>	The intervals, in milliseconds, in which to poll the state of the screen during bitmap synchronization. To use the standard Citrix client notifications instead of forced polling, specify 0.

## COM/DCOM > Filter Node

Enables you to define which COM/DCOM objects to record.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• Record &gt; Recording Options &gt; COM/DCOM &gt; Filter</li><li>• Replay &gt; Runtime Settings &gt; COM/DCOM &gt; Filter</li></ul>
------------------	--

User interface elements are described below:

UI Element	Description
<b>DCOM Profile</b>	<b>Specify one of the following filter types:</b> <ul style="list-style-type: none"><li>• <b>Default Filter.</b> The filter to be used as the default when recording a COM Vuser script.</li><li>• <b>New Filter.</b> A clean filter based on the default environment settings. Note that you must specify a name for this filter before you can record with its settings.</li></ul> You can also save the current settings and delete a filter using the <b>Save As</b> and <b>Delete</b> buttons.

UI Element	Description
<b>DCOM Listener Settings List</b>	<p>Displays a tree hierarchy of type libraries. You can expand the tree to show all of the available classes in the type library. You can expand the class tree to show all of the interfaces supported by that class.</p> <p>To exclude a type library, clear the check box next to the library name. This excludes all of its classes in that type library. By expanding the tree, you can exclude individual classes or interfaces by clearing the check box next to the item.</p> <p>An interface can be implemented differently by various classes. When you exclude an interface that is implemented by other classes that have not been excluded, a dialog box opens asking you if you also want to exclude the interface in all classes that implement it this interface.</p> <p>Note that when you clear the check box adjacent to an interface, it is equivalent to selecting it in the Excluded Interfaces dialog box.</p> <ul style="list-style-type: none"> <li>• <b>Environment.</b> The environments to record: ADO objects, RDS Objects, and Remote Objects. Clear the objects you do not want to record.</li> <li>• <b>Type Libraries.</b> A type library <b>.tlb</b> or <b>.dll</b> file, that represents the COM object to record. All COM objects have a type library that represents them. You can select a type library from the Registry, Microsoft Transaction Server, or file system.</li> </ul> <p><b>Type Libraries.</b> In the lower section of the dialog box, VuGen displays the following information for each type library.</p> <ul style="list-style-type: none"> <li>• <b>TypLib.</b> The name of the type library (tlb file).</li> <li>• <b>Path.</b> The path of the type library.</li> <li>• <b>Guid.</b> The Global Unique Identifier of the type library.</li> </ul>
<input data-bbox="311 1311 376 1343" type="button" value="Add"/>	<p>Adds another COM type library.</p> <ul style="list-style-type: none"> <li>• <b>Browse Registry.</b> Displays a list of type libraries found in the registry of the local computer. Select the check box next to the desired library or libraries and click <b>OK</b>.</li> <li>• <b>Browse file system.</b> Allows you to select type libraries from your local file system.</li> <li>• <b>Browse MTS.</b> add a component from a Microsoft Transaction Server. The MTS Components dialog box prompts you to enter the name of the MTS server.</li> </ul> <p>Type the name of the MTS server and click <b>Connect</b>. Remember that to record MTS components you need an MTS client installed on your machine. Select one or more packages of MTS components from the list of available packages and click <b>Add</b>. Once the package appears in the list of Type Libraries, you can select specific components from the package.</p>

UI Element	Description
 Remove	Removes a COM type library.
 Exclude...	<p>Excludes interfaces in the filter through the Excluded Interfaces dialog box. In this dialog box, the checked interface listings are the ones that are excluded. You can also add interfaces that are not listed. Click <b>Add Interface...</b> in the Excluded Interfaces dialog box and enter the GUID number (interface ID) and name of the interface. You can copy the GUID from the interfaces.h file created by VuGen and listed in the selection tree in the left-hand column of the VuGen screen. Use the <b>Add Interface...</b> feature to exclude interfaces that are called needlessly by the script, but are not listed anywhere in the filter.</p> <p>An interface can be implemented differently by various classes. When you exclude an interface that is implemented by other classes that have not been excluded, VuGen displays a warning. If you check <b>Don't ask me again</b> and close the dialog box, then the status of all instances of the interface in all other classes will be changed automatically for this filter, whenever you change the status of the interface in one object. Click <b>Yes to all</b> to change the status of all instances of this interface for all other classes, click <b>No to all</b> to leave the status of all other instances unchanged. Click <b>Next Instance</b> to view the next class that uses this interface.</p>

## COM/DCOM > Options Node

Enables you to set additional options for your COM recording session, relating to the handling of objects, generation of logs, and VARIANT definitions.

The DCOM scripting options apply to all programming languages. These settings let you configure the scripting options for DCOM methods and interface handling.

To access	VuGen > Replay > Run-time Settings > COM/DCOM > Options
-----------	---

User interface elements are described below:

UI Element	Description
<b>ADO Recordset filtering</b>	Condense multiple recordset operations into a single-line fetch statement (enabled by default).
<b>Declare Temporary VARIANTs as Globals</b>	Define temporary VARIANT types as Globals, not as local variables (enabled by default).
<b>Fill array in separate scopes</b>	Fill in each array in a separate scope (enabled by default).
<b>Fill structure in separate scopes</b>	Fill in each structure in a separate scope (enabled by default).

UI Element	Description
<b>Generate COM exceptions</b>	Generate COM functions and methods that raised exceptions during recording (disabled by default).
<b>Generate COM statistics</b>	Generate recording time performance statistics and summary information (disabled by default).
<b>Limit size of SafeArray log</b>	Limit the number of elements printed in the safearray log per COM call, to 16 (enabled by default).
<b>Release COM Objects</b>	Record the releasing of COM objects when they are no longer in use (enabled by default).
<b>Save Recordset content</b>	Stores Recordset content as grids, to allow viewing of recordset in VuGen (enabled by default).
<b>Trap binded moniker objects</b>	Trap all of the bound moniker objects (disabled by default).

## ***Data Format Extension > Configuration Node***

Enables Data Format Extensions during code generation.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Data Format Extension &gt; Configuration</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 246.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• "<a href="#">How to Apply DFE Chains to Sections of the HTTP Message</a>" on page 837</li><li>• "<a href="#">Implementing GWT-DFE Support</a>" on page 845</li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>• "<a href="#">Data Format Extensions (DFEs) - Overview</a>" on page 831</li><li>• "<a href="#">Data Format Extension List</a>" on page 839</li></ul>

User interface elements are described below:

UI Element	Description
<b>Enable data format extension</b>	Enables you to select chains for each message section of the HTTP message. Deselected by default.

## ***Flex > Configuration Node (Run-Time Settings)***

Enables you to set an external JVM (Java Virtual Machine) path.

To access	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Flex &gt; Configuration</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Use External JVM</b>	Enables you to use an external JVM. If you choose this option, you must specify the path:  <b>External JVM Path</b> The full path of the external JVM.
<b>Use GraniteDS configuration</b>	Defines the server side Data Service configuration.  If you select this option, do not select <b>Use Flex LCDS/BlazeDS jars</b> to serialize the messages in the <b>Externalizable</b> node.
<b>Maximum Formatted Request/Response size to print</b>	Enables you to specify the maximum character length of a request or response body to be captured in the log files. The option only affects the <b>flex_amf_call</b> and <b>flex_remoting_call</b> steps.  For example, if you specify a value of 1048576 characters (1MB), only responses or requests with a length less than a megabyte will be printed on the Code Generation or Replay log.

## Flex > RTMP Node

Enables you to set the Flex RTMP run-time settings.

To access	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Flex &gt; RTMP</b>
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Close all open RTMP connections after each iteration</b>	Automatically disconnects any open RTMP connections at the end of each iteration.

<b>TCP receive timeout (milliseconds)</b>	Specifies the time interval in milliseconds during which waits for the client to start receiving TCP/IP packets. If a timeout has been reached, triggers a warning or error depending on the run-time setting for <b>Status for TCP receive timeout</b> .
<b>Status for TCP receive timeout</b>	Indicates which status to issue for a step when timeout is exceeded.
<b>Warning</b>	Issues a warning for the step when the timeout is exceeded. continues to the next step.
<b>Error</b>	Issues an error for the step when the timeout is exceeded. The script ends.

## ***Flex > Externalizable Node (Run-Time Settings)***

The dialog box enables you to configure run time setting for externalizable objects in Flex scripts.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Flex &gt; Externalizable</b>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">How to Serialize Using External Java Serializer</a></li><li>• <a href="#">"How to Serialize Flex Scripts " on page 645</a></li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Flex Overview" on page 625</a></li><li>• <a href="#">" Externalizable Objects in Flex Scripts" on page 642</a></li></ul>

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Do not encode externalizable objects</b>	Run externalizable objects without encoding.

<b>Encode externalizable objects using</b>	Select the appropriate radio button: <ul style="list-style-type: none"><li>• <b>LoadRunner AMF serializer.</b> Use the Flex server parser to encode and decode externalizable objects. Select this option if you are not using the Adobe LiveCycle Data Services (LCDS) or Adobe BlazeDS server.</li><li>• <b>Custom Java classes.</b> Use an external parser to encode and decode externalizable objects. Select one or both of the following options:<ul style="list-style-type: none"><li>▪ <b>Use Flex LCDS/BlazeDS jars.</b> Use Flex LCDS or BlazeDS jars to serialize the messages. If you selected <b>UseGraniteDS configuration</b> in the <b>Configuration</b> node, do not enable this option.</li><li>▪ <b>Use additional jars.</b> Use Flex global jars to serialize the messages. Specify the full path to the jar file locations in the <b>Flex server/application jar file location(s)</b> box. Separate multiple entries with a semicolon. If your jars have the same names as the LCDS or BlazeDS jars, with the <b>Use Flex LCDS/BlazeDS jars</b> option enabled, they will be overwritten.</li></ul></li></ul>
--	--

## General > Additional Attributes Node

You can use the Additional Attributes node to provide additional arguments for a Vuser script. The Additional Attributes settings apply to all Vuser script types.

You specify command line arguments that you can retrieve at a later point during the test run, using `lr_get_attrib_string`. Using this node, you can pass external parameters to prepared scripts.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; General &gt; Additional Attributes</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Additional Attributes table>	A list of the additional attributes and their values.
 Add	Add a new argument.
 Remove	Remove an argument.

## General > Log Node

Enables you to configure the amount and types of information that is recorded in the log.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; General &gt; Log</b>
------------------	---

User interface elements are described below:

UI Element	Description
<b>Enable logging</b>	Enables automatic logging during replay. Disabling this option only affects automatic logging and log messages issued through <b>Ir_log_message</b> . Messages sent manually, using <b>Ir_message</b> , <b>Ir_output_message</b> , and <b>Ir_error_message</b> , are still issued.
<b>Log options</b>	Indicates when messages are sent to the log: <ul style="list-style-type: none"><li>• <b>Send messages only when an error occurs.</b> Sends messages to the log only when an error occurs. Click <b>Advanced</b> to configure the log cache size. If the contents of the cache exceed the specified size, VuGen deletes the oldest items.</li><li>• <b>Always send messages.</b> Sends all messages to the log.</li></ul>
<b>Standard log</b>	Creates a standard log of functions and messages sent during script execution to use for debugging. You can disable this option for large load testing scenarios or profiles if you wish to save system resources.
<b>Extended log</b>	Creates an extended log, including warnings and other messages. You can disable this option for large load testing scenarios or profiles if you wish to save system resources. You can also specify the following options: <ul style="list-style-type: none"><li>• <b>Parameter substitution.</b> Logs all parameters assigned to the script along with their values.</li><li>• <b>Data returned by server.</b> Logs all of the data returned by the server.</li><li>• <b>Advanced trace.</b> Logs all of the functions and messages sent by the Vuser during the session.</li></ul>



## General > Log Node (AjaxTruClient)

Enables you to configure the amount and types of information that is reported to a log for Ajax TruClient scripts.

To access

VuGen > Replay > Run-Time Settings > General > Log

User interface elements are described below:

UI Element	Description
<b>Log Level and Associated Options</b>	<p><b>Error-only</b></p> <ul style="list-style-type: none"><li>Select to log only error messages.</li></ul> <p><b>Standard log</b></p> <ul style="list-style-type: none"><li>Log errors/warnings only (in Standard log). Select to log errors and warnings only. Informative messages are not included.</li></ul> <p>In Extended log, all messages ignored due to this option are included, regardless of this setting.</p> <p><b>Extended Log</b></p> <ul style="list-style-type: none"><li>Select to log low-level informative messages and all messages included in the Standard log.</li></ul> <p><b>HTTP-related messages</b></p> <ul style="list-style-type: none"><li><b>Log HTTP request headers.</b> Log HTTP request header of each request.</li><li><b>Log HTTP request body (POST data).</b> Log the HTTP request body of each request.</li><li><b>Log HTTP response headers.</b> Log the HTTP response headers of each response.</li><li><b>Log HTTP response body.</b> Log the HTTP response body of each response.</li><li><b>Log HTTP trace.</b> Log the HTTP request/response handling Application under Test (AUT) messages</li></ul> <p><b>Application under test (AUT) messages</b></p> <ul style="list-style-type: none"><li><b>Log AUT error messages.</b> Logs error messages which are received from the application under test.</li><li><b>Log AUT non-error messages.</b> Log informative messages which are received from the application under test.</li></ul> <p><b>Parameterization</b></p> <ul style="list-style-type: none"><li><b>Log Parameter substitution.</b> Logs the parameters and the values used when the Vuser script runs.</li></ul>

UI Element	Description
Create a log file only if required	<b>Accumulate messages in memory, write only if required.</b> <ul style="list-style-type: none"><li>Select to log messages only when an error occurs.</li><li><b>Accumulate Messages in Memory Buffer Size.</b> Enter the memory buffer size where important messages are logged.  <b>Note:</b> If the size is too small, messages will be lost. If the size is too large, this may contribute to paging issues and slow execution.</li></ul>
Log Message Formatting Options	<b>User Log Line Length.</b> <ul style="list-style-type: none"><li>Enter the limit for a single line in a user log file before the message line begins to wrap.</li></ul> <b>Include Timestamps in user log.</b> <ul style="list-style-type: none"><li>Select to include time trace to each message in the log.</li></ul>
Internal Support Options	These options are for use with a customer support representative only. Do no modify them unless specifically instructed to do so by customer support.



## General > Advanced Settings (TruClient)

This dialog box enables you to configure advanced settings for TruClient Ajax - Mobile.

To access	VuGen > Replay > Run-Time Settings > General > Advanced Settings
-----------	--

User interface elements are described below:

UI Element	Description
Enable Plugin Support	If selected, enables plug in support, such as Flash.

## Load > Browser Settings Node (Ajax TruClient)

This node enables you to configure settings for the Ajax TruClient browser for scripts that you run in load mode.

To access	VuGen > Replay > Run-Time Settings > Load > Browser Settings
<b>Important information</b>	<ul style="list-style-type: none"><li>Settings that you modify in the Load Mode Browser Settings node affect load mode only.</li><li>The settings available in the Load Mode Browser Settings node are the same settings that are available in the "<a href="#">"TruClient General Settings Dialog Box" on page 562</a>.</li><li>Settings that you modify in the Browser Settings tab affect interactive mode only. When you save your script in interactive mode, any settings that you modified in the Browser Settings tab are applied to the Load Mode Browser Settings.</li></ul>



## FireFox Browser Settings

User interface elements are described below:

UI Element	Description
<b>Proxy selection</b>	
<b>No proxy (direct connection to the internet)</b>	For all Vusers, make the connection to the Internet directly without using a proxy server.
<b>Use system proxy settings</b>	(Default) Use system configuration for proxy settings.
<b>Manual proxy configuration</b>	Enables you to set and configure proxy server settings.
<b>Do not use a proxy for (exceptions)</b>	You can specify exceptions to the proxy server rules. You can list the exceptions as hostnames, IPs and/or masks. <b>Note:</b> You can use wildcards as part of the hostname, e.g. *.devlab.ad.
<b>Host for HTTP/all protocols</b>	The domain name or IP address of the proxy server used for HTTP and other protocol requests.
<b>Port for HTTP/all protocols</b>	The port number of the proxy server used for HTTP and other protocol requests.
<b>Use separate proxy for HTTPS protocol</b>	Enables you to use a separate proxy server to handle all HTTPS protocol requests.
<b>Host for HTTPS protocol</b>	The domain name or IP address of the proxy server used for HTTPS protocol requests.

UI Element	Description
<b>Port for HTTPS protocol</b>	The port number of the proxy server used for HTTPS protocol requests.
<b>AUTOMATIC proxy configuration (PAC)</b>	Automatically read the proxy settings from the proxy auto configuration file (PAC). In the <b>URL</b> field, enter the URL of the PAC file.
<b>Advanced</b>	
<b>Home Page URL</b>	Enter the URL to navigate to when window home is called from JavaScript. (about:blank by default)
<b>User-Agent</b>	Enter the User-Agent string for overriding the browser default in request headers.
<b>Compare the page in cache to the page on the network</b>	<p>Enter the corresponding number used to compare the URL page in the cache to the URL page called from the network.</p> <ul style="list-style-type: none"> <li>• <b>0.</b> (Default) Once per session.</li> <li>• <b>1.</b> Every time the page is accessed.</li> <li>• <b>2.</b> Never.</li> <li>• <b>3.</b> When the page is out of date (default).</li> </ul>
<b>Keep-Alive</b>	<p>Allows persistent (non-proxied) network connections.</p> <ul style="list-style-type: none"> <li>• <b>Checked.</b> (Default) Allow persistent (non-proxied) network connections, so that the open connections can be reused.</li> <li>• <b>Cleared.</b> Close each connection after the request is complete.</li> </ul>
<b>Proxy Keep-Alive</b>	<p>Allows persistent proxy connections.</p> <ul style="list-style-type: none"> <li>• <b>Checked.</b> (Default) Allow persistent proxy connections, so that open connections can be reused.</li> <li>• <b>Cleared.</b> Close each connection after the request is complete.</li> </ul>
<b>Keep-Alive timeout (sec)</b>	Enter the number of seconds to keep idle connections open. (300 by default)
<b>HTTP version</b>	Enter the HTTP version to use when accessing the network/application not via a proxy. (1.1 by default)
<b>Proxy HTTP version</b>	Enter the Proxy HTTP version to use when accessing the network/application via a proxy. (1.1 by default)

UI Element	Description
<b>DNS cache entries</b>	Enter the maximum number of entries to keep in the DNS cache. Enter 0 to disable this option. (20 by default)
<b>SSL</b>	Select the secure connection settings: <ul style="list-style-type: none"> <li>• SSL 2.0</li> <li>• (Default) SSL 3.0</li> <li>• (Default) TLS 1.0</li> </ul>



## IE Browser Settings

User interface elements are described below:

UI Element	Description
<b>Proxy selection</b>	
<b>No proxy (direct connection to the internet)</b>	For all Vusers, make the connection to the Internet directly without using a proxy server.
<b>Use system proxy settings</b>	(Default) Use system configuration for proxy settings.
<b>Use automatic configuration script (PAC)</b>	Automatically read the proxy settings from the proxy auto configuration file (PAC). In the <b>Address</b> field, enter the URL of the PAC file.
<b>Use Manual proxy server for your LAN</b>	<p><b>Address: Port.</b> Use format 'Address:port'</p> <p><b>Do not use proxy server for addresses beginning with.</b> Use semicolons (;) to separate entries.</p> <p><b>Bypass proxy server for local addresses.</b> Do not use proxy for addresses in your LAN.</p> <p><b>Do not use the same proxy server for all protocols.</b> Enter a proxy for at least one of the protocols.</p>
<b>Advanced</b>	
<b>Keep-Alive timeout (milliseconds)</b>	Timeout (in milliseconds) for keeping idle connections open(applies to both direct and proxied connections)
<b>Server info timeout (milliseconds)</b>	Timeout (in milliseconds) for data to be returned from the server. This setting should be changed if the Keep-Alive timeout is more than 2 minutes (120,000 seconds).

UI Element	Description
<b>DNS cache timeout</b>	Timeout (in milliseconds) that DNS entries are cached.
<b>Start Page</b>	The URL to navigate to when window home is called from JavaScript. (about:blank by default)
<b>User-Agent</b>	The User-Agent string for overriding the browser default in request headers. Leave blank to use the default user agent of IE.
<b>HTTP 1.1 settings</b>	<p>The port number of the proxy server used for HTTP and other protocol requests.</p> <ul style="list-style-type: none"> <li>• Use HTTP 1.1</li> <li>• Use HTTP 1.1 through proxy connections</li> </ul>
<b>SSL</b>	<p>Select the secure connection setting(s):</p> <ul style="list-style-type: none"> <li>• <b>Use SSL 2.0.</b> Enable SSL 2.0 for secure connections.</li> <li>• <b>Use SSL 3.0.</b> Enable SSL 3.0 for secure connections.</li> <li>• <b>Use TLS 1.0.</b> Enable TLS 1.0 for secure connections.</li> <li>• <b>Use TLS 1.1.</b> Enable TLS 1.1 for secure connections.</li> <li>• <b>Use TLS 1.2.</b> Enable TLS 1.2 for secure connections.</li> </ul>
<b>Temporary Internet Files</b>	<p>Configure when IE will compare the local copy of the resource (cache) to the network.</p> <p>Check for newer version of stored pages:</p> <ul style="list-style-type: none"> <li>• <b>Every time I visit the webpage.</b> The resource is checked on every request.</li> <li>• <b>Every time I start Internet Explorer.</b> The resource is checked on browser start.</li> <li>• <b>Automatically.</b></li> <li>• <b>Never.</b></li> </ul>



## Load > Other Settings (TruClient)

This dialog box enables you to configure snapshot generation and action on error for TruClient.

To access

VuGen > Replay > Run-Time Settings > Load > Other Settings

User interface elements are described below:

UI Element	Description
<b>Snapshot Generation</b>	
<b>Replay snapshots generation</b>	<b>Never.</b> If selected, snapshots are never generated on replay. <b>On Error.</b> If selected, snapshots are generated on steps with errors during replay. <b>Always.</b> If selected, snapshots are generated on all steps in the script during replay.
<b>Action on error</b>	<b>Abort script.</b> Select to abort running script when an error occurs. <b>Continue to the next iteration.</b> Select to stop current iteration and continue to the next one.

## General > Replay Node

### All Protocols - Except Mobile Ajax TruClient

To access	VuGen > Replay > Run-Time Settings > General > Replay
UI Element	Description
<b>Simulate a new user on each iteration</b>	Instructs VuGen to reset all HTTP contexts between iterations. This setting allows the Vuser to more accurately emulate a new user beginning a browsing session. <b>Default value:</b> enabled.

UI Element	Description
Proxy selection	<p>The settings in this section apply to both recording and running the script. They apply to this script only. To configure proxy settings for all Ajax TruClient scripts, open the <b>Browser Configuration Settings</b> dialog box. For more information, see "<a href="#">TruClient General Settings Dialog Box</a>" on page 562.</p> <p><b>Retrieve global proxy settings (defined in Ajax TruClient Browser Options).</b></p> <p>Select to use the proxy settings defined in the Browser Options dialog box. The settings are retrieved when you click Develop Script. Once global proxy settings are retrieved, they are copied to the script's run-time settings and can be managed in the "Define proxy settings for script" section.</p> <p><b>Define specific proxy settings for the script.</b></p> <ul style="list-style-type: none"><li>• No proxy (direct connection to the internet). For all Vusers, make the connection to the Internet directly without using a proxy server.</li><li>• Manual proxy configuration. If selected, you can specify exceptions to the proxy server rules, specify the proxy server for all HTTP/HTTPS connections. You require a separate proxy server for HTTP connections, check <b>Use separate proxy for HTTPS protocol</b> box and specify the proxy server settings.</li><li>• AUTOMATIC proxy configuration (PAC). If selected, the proxy settings are automatically read from the proxy auto configuration file (PAC). In the URL field, enter the URL of the PAC file.</li></ul> <p><b>Note:</b> If you are using a PAC file for proxy configuration, it is required that the PAC script directs 127.0.0.1 to a direct connection and not through a proxy.</p>

UI Element	Description
<b>Snapshots generation</b>	<p><b>Recording snapshots generation</b></p> <ul style="list-style-type: none"> <li>Never. If selected, recording snapshots of the script are not automatically saved.</li> <li>Always. If selected, recording snapshots are automatically saved for every step in the script.</li> </ul> <p><b>Replay snapshots generation</b></p> <ul style="list-style-type: none"> <li>Never. If selected replay snapshots are not generated. <b>Note:</b> This is the default setting.</li> <li>On error. Select to generate a snapshot when errors occurs. This option can be used to help identify bugs in your script. For more information, see Debug Scripts Using Snapshots.</li> <li>Always. If selected snapshots are generated for every step in the script.</li> </ul>
<b>Action on error</b>	<p><b>Abort script</b> Select to abort running script when an error occurs.</p> <p><b>Continue to the next iteration</b> Select to stop iteration when an error occurs and continue to the next one.</p>
<b>Replay Options</b>	<p><b>Maximum time for object-not-found (seconds)</b> Enter the maximum time to search for an object before the application displays an error message.</p> <p><b>Inter-step interval (milliseconds)</b> Enter the minimal interval between steps. Specifying a higher value can help with synchronization issues, but too high a value may slow the script more than necessary.</p> <p><b>End-of-network identification timeout (milliseconds)</b> The end-of-network for a step is recognized when the specified time has elapsed with no networking activity.</p>

UI Element	Description
<b>Advanced</b>	<p>A number of options for advanced users. For more details, read the tips displayed at the bottom of the Run-Time settings dialog box:</p> <ul style="list-style-type: none"> <li>• <b>Home Page URL.</b> Enter the URL to navigate to when window home is called from JavaScript.</li> <li>• <b>User-Agent.</b> Enter the User-Agent string for overriding the browser default in request headers.</li> <li>• <b>Compare the page in cache to the page on the network.</b> Enter the corresponding number used to compare the URL page in the cache to the URL page called from the network. 0=Once per session, 1=Every time the page is accessed, 2=Never, 3=When the page is out of date (default).</li> <li>• <b>Keep-Alive.</b> Select to allow persistent (non-proxied) network connections. Enter the following corresponding number: 1=Allow persistent (non-proxied) network connections, so that the open connections can be reused, 0=Close each connection after the request is complete.</li> <li>• <b>Proxy Keep-Alive.</b> Select to allow persistent proxy connections. Enter the following corresponding number: 1=Allow persistent proxy connections, so that open connections can be reused. 0=Close each connection after the request is complete.</li> <li>• <b>Keep-Alive timeout (sec).</b> Enter the number of seconds to keep idle connections open.</li> <li>• <b>HTTP version.</b> Enter the HTTP version to use when accessing the network/application not via a proxy.</li> <li>• <b>Proxy HTTP version.</b> Enter the Proxy HTTP version to use when accessing the network/application via a proxy.</li> <li>• <b>DNS cache entries.</b> Enter the max number of entries to keep in the DNS cache.</li> </ul> <p><b>Note:</b> Enter 0 to disable this option.</p> <ul style="list-style-type: none"> <li>• <b>Non-interactive window size.</b> Enter the initial dimensions (width and height in pixels) of the browser window in non-interactive mode.</li> <li>• <b>SSL.</b> Select the secure connection setting/s: <ul style="list-style-type: none"> <li>■ SSL 2.0</li> <li>■ SSL 3.0</li> <li>■ TLS 1.0</li> </ul> </li> </ul>

## Mobile Ajax TruClient

UI Element	Description
<b>Simulate a new user on each iteration</b>	Instructs VuGen to reset all HTTP contexts between iterations. This setting allows the Vuser to more accurately emulate a new user beginning a browsing session. <b>Default value:</b> enabled.
<b>Replay Options</b>	
<b>Replay using recorded duration for steps</b>	During replay, each step's minimum time of running will be as recorded.  <b>Note:</b> After editing the script, this might cause false timing of steps in the script.
<b>Failed event causes step failure</b>	If the <b>End Event</b> of a step fails, the step will fail. For example, if the <b>End Event</b> of a step is <b>Document Loaded</b> and the document fails to load, the step will fail.  This option is enabled by default.
<b>Enable profiling</b>	Enable/disable profiling for client side breakdown.  <b>Maximum time for object-not-found (seconds)</b> Enter the maximum time to search for an object before the application displays an error message.  <b>Step timeout</b> The amount of time to perform a step. If the End Event does not occur by this time the step fails.  <b>Inter-step interval (milliseconds)</b> Enter the minimal interval between steps. Specifying a higher value can help with synchronization issues, but too high a value may slow the script more than necessary.  <b>End-of-network identification timeout (milliseconds)</b> The end-of-network for a step is recognized when the specified time has elapsed with no networking activity.  <b>Typing interval (milliseconds)</b> The average amount of time between keystrokes when entering text during replay.

UI Element	Description
<b>Minimum Time</b>	<p><b>Random step's minimum time within range.</b></p> <p>During replay, each step's minimum time settings will be overridden by a randomized value.</p> <p><b>From (percentage).</b> Set lower percentage.</p> <p><b>To (percentage).</b> Set upper percentage.</p> <p><b>Limit step's minimum time.</b> Set the step's minimum time value in seconds.</p> <p><b>Apply minimum time setting on wait steps.</b> Enable/disable applying minimum time setting on wait steps.</p>
<b>Automatic transactions</b>	<p><b>No automatic transactions.</b> Do not apply automatic transactions.</p> <p><b>Define each action as a transaction..</b> Treat each action in the script as a transaction for performance measurements.</p> <p><b>Define each action as step as a transaction.</b> Treat each action and step in as a transaction for performance measurements.</p>

## General > Miscellaneous Node

Enables you to set miscellaneous run-time settings.

To access	VuGen > Replay > Run-Time Settings > General > Miscellaneous
<b>Important information</b>	<ul style="list-style-type: none"> <li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 320</a>.</li> <li>We do not recommend enabling both the <b>Continue on Error</b> and <b>Generate Snapshot on Error</b> options in a load test environment. This configuration may adversely affect the Vusers' performance.</li> <li>If you require the Vusers to generate breakdown data for diagnostics (J2EE) during the scenario run, do not use automatic transactions. Instead, manually define the beginning and end of each transaction.</li> </ul>

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Automatic Transactions</b>	<ul style="list-style-type: none"> <li><b>Define each action as a transaction.</b> Instructs LoadRunner (not applicable to HP Business Service Management) to handle every action in the script as a transaction.</li> <li><b>Define each step as a transaction.</b> Instructs LoadRunner (not applicable to HP Business Service Management) to handle every step in the script as a transaction.</li> </ul>
<b>Error Handling</b>	<ul style="list-style-type: none"> <li><b>Continue on Error.</b> Continue script execution when an error occurs.</li> </ul> <p><b>Default value:</b> disabled.</p> <ul style="list-style-type: none"> <li><b>Fail open transactions on Ir_error_message.</b> Instructs VuGen to mark all transactions in which an <code>Ir_error_message</code> function was issued, as <i>Failed</i>. The <code>Ir_error_message</code> function is issued through a manually defined <code>If</code> statement.</li> <li><b>Generate Snapshot on Error.</b> Generates a snapshot when an error occurs. You can see the snapshot by viewing the Vuser Log and double-clicking on the line at which the error occurred.</li> </ul>
<b>Multithreading</b>	<ul style="list-style-type: none"> <li><b>Run Vuser as a process.</b> Disables multithreading.</li> <li><b>Run Vuser as a thread.</b> Enables multithreading.</li> </ul> <p>For details, see "<a href="#">Multithreading</a>" on page 320.</p>

## General > Pacing Node

Allows you to control the time between iterations. The pace tells the Vuser how long to wait between iterations of your actions.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; General &gt; Pacing</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>After the previous iteration ends</b>	Starts each new iteration a specified amount of time after the end of the previous iteration. Specify either an exact number of seconds or a range of time.
<b>As soon as the previous iteration ends</b>	The new iteration begins as soon as possible after the previous iteration ends.
<b>At &lt;fixed/random&gt; intervals</b>	You specify the time between iteration—either a fixed number of seconds or a range of seconds from the beginning of the previous iteration. Each scheduled iteration will only begin when the previous iteration is complete.

## General > Run Logic Node

Enables you to set the run logic run-time settings.

To access	VuGen > Replay > Run-Time Settings > General > Run Logic
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.
See also	" <a href="#">Vuser Script Sections</a> " on page 255

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Inserts a new Action at the insertion point.
	Inserts a new Action block at the insertion point.
	Deletes an item.
	Moves an item up.
	Moves an item down.
	Opens the Properties Dialog Box enabling you to set the run logic and iterations settings. <b>Run Logic.</b> Configures the action to run sequentially or randomly. <b>Iterations.</b> Sets the number of times an item will run.
<Run logic tree>	A graphical illustration of the run logic for this script.
Number of Iterations	The number of times the script will run of the items in the run logic tree.

## General > Think Time Node

Enables you to configure the think time settings, controlling the time that a VuGen waits between actions. These settings are designed to help you emulate a real user.

To access	VuGen > Replay > Run-Time Settings > General > Think Time
See also	<ul style="list-style-type: none"><li>VuGen uses <b>lr_think_time</b> functions to record think time values into your Vuser scripts. For more information about the <b>lr_think_time</b> function and how to modify it manually, see the Function Reference (Help &gt; Function Reference).</li></ul>

User interface elements are described below:

UI Element	Description
<b>As recorded</b>	During replay, use the argument that appears in the <code>lr_think_time</code> function. For example, <code>lr_think_time(10)</code> waits ten seconds.
<b>Ignore think time</b>	Ignore the recorded think time—replay the script ignoring all <code>lr_think_time</code> functions.
<b>Limit think time to</b>	Limit the think time's maximum value.
<b>Multiply recorded think time by</b>	During replay, use a multiple of the recorded think time. This can increase or decrease the think time applied during playback. For example, if a think time of four seconds was recorded, you can instruct your Vuser to multiply that value by two, for a total of eight seconds. To reduce the think time to two seconds, multiply the recorded time by 0.5.
<b>Replay the think time</b>	Enables options which let you customize the recorded think times.
<b>Use random percentage of recorded think time</b>	Use a random percentage of the recorded think time. You set a range for the think time value by specifying a range for the think time. For example, if the think time argument is 4, and you specify a minimum of 50% and a maximum of 150%, the lowest think time can be two (50%) and the highest value six (150%).

## Internet Protocol > ContentCheck Node

Enables you to check websites for content during run-time.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Internet Protocol &gt; ContentCheck</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Deletes the selected rule or application.
	Exports rules to an xml file.
	Imports rules from an existing xml file.
	Adds a new application to the list of applications and rules. Click to change the name.

UI Element	Description
<b>New Rule</b>	<p>Displays the rule criteria in the right pane, allowing you to enter a new rule for the currently selected application.</p> <ul style="list-style-type: none"> <li><b>Search for text.</b> The text of the string for which you want to search.</li> <li><b>Search by prefix and suffix.</b> The prefix and suffix of the string for which you want to search.</li> <li><b>Match case.</b> Perform a case sensitive search.</li> <li><b>Fail if.</b> Configure the results of the search to fail if the string is either found or not found.</li> <li><b>Search JavaScript alert box text.</b> Only search for text within JavaScript alert boxes (Web and Oracle Web Applications 11i Vusers only).</li> </ul>
<b>Set as Default...</b>	Set the ContentCheck configuration as default (i.e. new scripts will start with this configuration).
<b>&lt;Application and Rule list&gt;</b>	A list of applications and rules. You can enable and disable individual items by using the check boxes to the left of each item.
<b>Enable ContentCheck during replay</b>	Enable content checking during replay. Note that even after you define applications, you can disable it for a specific test run, by disabling this option. <b>Default value:</b> enabled.

## Internet Protocol > Download Filters Node

Enables you to set the download filters.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Internet Protocol &gt; Download Filters</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>&lt;Filter list&gt;</b>	A list of filters for the script. Each filter has a type and data. For example, a filter of type URL would have a URL address as its data. You can <b>Add</b> , <b>Edit</b> , <b>Remove</b> , or <b>Remove All</b> entries in the list.

<b>Exclude addresses in list</b>	Ignore requests from the listed sites or hosts.
<b>Include only addresses in list</b>	Restrict replay to the listed sites or hosts.

## **Internet Protocol > Preferences Node**

Enables you to set various internet related run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Internet Protocol &gt; Preferences</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Checks</b>	<ul style="list-style-type: none"><li><b>Enable Image and Text Check.</b> Allows the Vuser to perform verification checks during replay by executing the verification functions <code>web_find</code> or <code>web_image_check</code>. This option only applies to statements recorded in HTML-based mode. Vusers running with verification checks use more memory than Vusers who do not perform checks.</li></ul> <p><b>Default value:</b> disabled.</p>
<b>Generate Web Performance Graphs</b>	Instructs a Vuser to collect data used to create Web Performance graphs. You view the <b>Hits per Second</b> , <b>Pages per Second</b> , and <b>Response Bytes per Second</b> (Throughput) graphs during test execution using the online monitors and after test execution using the Analysis. You view the Component Breakdown graph after test execution using the Analysis. Select the types of graph data for the Vuser to collect. <p><b>Note:</b> If you do not use the Web performance graphs, disable these options to save memory.</p>

UI Element	Description
Advanced	<ul style="list-style-type: none"> <li>• <b>WinInet Replay.</b> Instructs VuGen to use the WinInet replay engine instead of the standard Sockets replay. VuGen has two HTTP replay engines: Sockets-based (default) or WinInet based. The WinInet is the engine used by Internet Explorer and it supports all of the features incorporated into the IE browser. The limitations of the WinInet replay engine are that it is not scalable and does not support Linux. In addition, when working with threads, the WinInet engine does not accurately emulate the modem speed and number of connections. VuGen's proprietary sockets-based replay is a lighter engine that is scalable for load testing. It is also accurate when working with threads. The limitation of the sockets-based engine is that it does not support SOCKS proxy. If you are recording in that type of environment, use the WinInet replay engine.</li> </ul> <p><b>Default value:</b> disabled (socket-based replay engine).</p> <ul style="list-style-type: none"> <li>• <b>File and line in automatic transaction names.</b> Creates unique transaction names for automatic transactions by adding file name and line number to the transaction name.</li> </ul> <p><b>Default value:</b> enabled.</p> <ul style="list-style-type: none"> <li>• <b>Non-critical item errors as warnings.</b> This option returns a warning status for a function which failed on an item that is not critical for load testing, such as an image or Java applet that failed to download. This option is enabled by default. If you want a certain warning to be considered an error and fail your test, you can disable this option. You can set a content-type to be critical by adding it to the list of Non-Resources. For more information, see "<a href="#">Non-Resources Dialog Box</a>" on page 212.</li> <li>• <b>Save snapshot resources locally.</b> Instructs VuGen to save the snapshot resources to files on the local machine.</li> <li>• <b>Options...</b> . Opens the "<a href="#">Advanced Options Dialog Box</a>" below.</li> </ul>

## Advanced Options Dialog Box

Enables you to set the advanced internet preference run-time settings.

To access	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Internet Protocol &gt; Preferences &gt; Options</b>
Important information	<ul style="list-style-type: none"> <li>• This dialog box is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on page 320.</li> <li>• This dialog box divides the properties into different categories: <b>HTTP</b>, <b>General</b>, <b>Authentication</b>, <b>Log</b>, and <b>Web (Click &amp; Script) Specific</b>.</li> </ul>

## HTTP

User interface elements are described below:

UI Element	Description
<b>HTTP version</b>	<p>Specifies which version HTTP to use: version 1.0 or 1.1. This information is included in the HTTP request header whenever a Vuser sends a request to a Web server.</p> <p><b>Default value:</b> HTTP 1.1.</p> <p>HTTP 1.1 supports the following features:</p> <ul style="list-style-type: none"><li>• Persistent Connections—see "Keep-Alive HTTP connections" below.</li><li>• HTML compression—see <a href="#">Accept Server-Side Compression</a> below.</li><li>• Virtual Hosting—multiple domain names sharing the same IP address.</li></ul>
<b>Keep-Alive HTTP connections</b>	<p>Keep-alive is a term used for an HTTP extension that allows persistent or continuous connections. These long-lived HTTP sessions allow multiple requests to be sent over the same TCP connection. This improves the performance of the Web server and clients.</p> <p>The keep-alive option works only with Web servers that support keep-alive connections. This setting specifies that all Vusers that run the Vuser script have keep-alive HTTP connections enabled.</p> <p><b>Default value:</b> enabled.</p>
<b>Accept-Language request header</b>	<p>Provides a comma-separated list of accepted languages. For example, <b>en-us</b>, <b>fr</b>, and so forth. For more details, see <a href="#">"Page Request Header Language" on page 1000</a>.</p>
<b>HTTP errors as warnings</b>	<p>Issues a warning instead of an error upon failing to download resources due to an HTTP error.</p>
<b>HTTP-request connect timeout (seconds)</b>	<p>The time, in seconds, that a Vuser will wait for the connection of a specific HTTP request within a step before aborting. Timeouts provide an opportunity for the server to stabilize and respond to the user. Note that this timeout also applies to the time the Vuser will wait for a WAP connection, initiated by the <b>wap_connect</b> function.</p> <p><b>Maximum value:</b> 32000 seconds.</p>
<b>HTTP-request receive timeout (seconds)</b>	<p>The time, in seconds, that a Vuser will wait to receive the response of a specific HTTP request within a step before aborting. Timeouts provide an opportunity for the server to stabilize and respond to the user.</p> <p><b>Maximum value:</b> 32000 seconds.</p>

UI Element	Description
<b>Request Zlib Headers</b>	Sends request data to the server with the <b>zlib</b> compression library headers. By default, requests sent to the server include the <b>zlib</b> headers. This option lets you emulate non-browser applications that do not include <b>zlib</b> headers in their requests. To exclude these headers, set this option to <b>No</b> . <b>Default value:</b> Yes.
<b>Accept Server-Side Compression</b>	Indicate to the server that the replay can accept compressed data. The available options are: <b>None</b> (no compression), <b>gzip</b> (accept gzip compression), <b>gzip, deflate</b> (accept gzip or deflate compression), and <b>deflate</b> (accept deflate compression). Note that by accepting compressed data, you may significantly increase the CPU consumption. <b>Default value:</b> Accept <b>gzip</b> and <b>deflate</b> compression. To manually add compression, enter the following function at the beginning of the script: <code>web_add_auto_header("Accept-Encoding", "gzip");</code> To verify that the server sent compressed data, search for the string Content - Encoding: gzip in the section of the server's responses of the replay log. The log also shows the data size before and after decompression.
<b>Delete unreferenced cache entries</b>	Delete cache entries that have not been referenced within the specified number of iterations. Set to zero (0) to never delete cache entries.

## General

User interface elements are described below:

UI Element	Description
<b>DNS caching</b>	Instructs the Vuser to save a host's IP addresses to a cache after resolving its value from the Domain Name Server. This saves time in subsequent calls to the same server. In situations where the IP address changes, as with certain load balancing techniques, be sure to disable this option to prevent Vuser from using the value in the cache. <b>Default value:</b> enabled.
<b>Convert from/to UTF-8</b>	Converts received HTML pages and submitted data from and to UTF-8. You enable UTF-8 support in the recording options. For more information, see <a href="#">"Recording Options" on page 176</a> . <b>Default value:</b> no.
<b>Step timeout caused by resources is a warning</b>	Issues a warning instead of an error when a timeout occurs due to a resource that did not load within the timeout interval. For non-resources, VuGen issues an error. <b>Default value:</b> disabled.

UI Element	Description
<b>Parse HTML Content-Type</b>	<p>When expecting HTML, parse the response only when it is the specified content-type: <b>HTML</b>, <b>text\html</b>, <b>TEXT</b> any text, or <b>ANY</b>, any content-type. Note that text/xml is not parsed as HTML.</p> <p><b>Default value:</b> <b>TEXT</b>.</p> <p>The timeout settings are primarily for advanced users who have determined that acceptable timeout values should be different for their environment. The default settings should be sufficient in most cases. If the server does not respond in a reasonable amount of time, check for other connection-related issues, rather than setting a very long timeout which could cause the scripts to wait unnecessarily.</p>
<b>Step download timeout (sec)</b>	<p>The time that the Vuser will wait before aborting a step in the script. This option can be used to emulate a user behavior of not waiting for more than x seconds for a page.</p> <p><b>Maximum value:</b> 32000 seconds.</p>
<b>Network buffer size</b>	<p>Sets the maximum size of the buffer used to receive the HTTP response. If the size of the data is larger than the specified size, the server will send the data in chunks, increasing the overhead of the system. When running multiple Vusers from the Controller, every Vuser uses its own network buffer. This setting is primarily for advanced users who have determined that the network buffer size may affect their script's performance. The default is 12K bytes. The maximum size is 0x7FFF FFFF.</p>
<b>Print NTLM information</b>	<p>Print information about the NTLM handshake to the standard log.</p>
<b>Print SSL information</b>	<p>Print information about the SSL handshake to the standard log.</p>
<b>Max number of error matches issued as ERRORS</b>	<p>Limits the number of error matches issued as ERRORS for content checks using a LB or RB (left boundary or right boundary). This applies to matches where a failure occurs when the string is found (Fail=Found). All subsequent matches are listed as informational messages.</p> <p><b>Default value:</b> 10 matches.</p>
<b>Maximum number of META Refresh to the same page</b>	<p>The maximum number of times that a META refresh can be performed per page.</p> <p><b>Default value:</b> 2.</p>
<b>ContentCheck values in UTF-8</b>	<p>Store the values in the ContentCheck XML file in UTF-8.</p>

UI Element	Description
<b>Tree-View request body limit</b>	Limit the number of request body bytes displayed in Tree-View. Set to zero (0) for no limit.
<b>IP Version</b>	The IP version to be used: IPv4, IPv6 or automatic selection. The default value is IPv4.
<b>web-sync retry interval (millisec)</b>	The time to wait (in milliseconds) between testing the condition that yields false and the next retry. The default value is 1000.
<b>web-sync retry timeout (millisec)</b>	The maximum time (in milliseconds) during which retries are allowed. If the computed timeout exceeds the step timeout (as determined by the 'Step download timeout' setting), the latter is used.

## Authentication

User interface elements are described below:

UI Element	Description
<b>Fixed think time upon authentication retry (msec)</b>	Automatically adds a think time to the Vuser script for emulating a user entering authentication information (username and password). This think time will be included in the transaction time. <b>Default value:</b> 0.
<b>Disable NTLM2 session security</b>	Use full NTLM 2 handshake security instead of the more basic NTLM 2 session security response. <b>Default value:</b> No.
<b>Use Windows native NTLM implementation</b>	Use the Microsoft Security API for NTLM authentication instead of the indigenous one. <b>Default value:</b> No.
<b>Override credentials in Windows native NTML implementation</b>	Use the credentials provided by the user at logon.
<b>Enable integrated Authentication</b>	Enable Kerberos-based authentication. When the server proposes authentication schemes, use <b>Negotiate</b> in preference to other schemes. <b>Default value:</b> No.

UI Element	Description
<b>Induce heavy KDC load</b>	Do not reuse credentials obtained in previous iterations. Enabling this setting will increase the load on the KDC (Key Distribution Server). To lower the load on the server, set this option to <b>Yes</b> in order to reuse the credentials obtained in previous iterations. This option is only relevant when Kerberos authentication is used. <b>Default value:</b> No.
<b>Use canonical name in SPN</b>	Use the canonical name instead of the original hostname retrieved from the URL, to generate SPN (Service Principal Name). <b>Default value:</b> Yes.
<b>Append non-default port to SPN</b>	Append the port number to the SPN, if the specified port is a non-standard one(neither 80 nor 443). <b>Default value:</b> No.
<b>Enable retrieving key from nCipher HSM</b>	Enables LoadRunner to retrieve private keys from the HSM (Hardware Security Module), such as nCipher. <b>Default value:</b> Yes.

## Log

User interface elements are described below:

UI Element	Description
<b>Print buffer line length</b>	Line length for printing request/response header/body and/or JavaScript source, disabling wrapping.
<b>Print buffer escape only binary zeros</b>	<ul style="list-style-type: none"><li><b>Yes.</b> Escape only binary zeros when printing request/response headers/body and/or JavaScript source.</li><li><b>No.</b> Escape any unprintable/control characters.</li></ul>

## Web (Click & Script) Specific (Replay only for version 12 and later)

User interface elements are described below:

UI Element	Description
General	<ul style="list-style-type: none"><li>• <b>Home Page URL.</b> The URL of the home page that opens with your browser (default is about:blank).</li><li>• <b>DOM-based snapshots.</b> Instructs VuGen to generate snapshots from the DOM instead of from the server responses.</li></ul> <p><b>Default value:</b> Yes.</p> <ul style="list-style-type: none"><li>• <b>Charset conversions by HTTP.</b> Perform charset conversions by the 'Content-Type:....; charset=...' HTTP response header. Overrides 'Convert from /to UTF-8.'</li><li>• <b>Reparse when META changes charset.</b> Reparse HTML when a META tag changes the charset. Effective only when <b>Charset conversions by HTTP</b> is enabled. <b>Auto</b> means reparsing is enabled only if it used in the first iteration.</li><li>• <b>Fail on JavaScript error.</b> Fails the Vuser when a JavaScript evaluation error occurs.</li></ul> <p><b>Default value:</b> No (issue a warning message only after a JavaScript error, but continue to run the script).</p> <ul style="list-style-type: none"><li>• <b>Initialize standard classes for each new window project.</b> When enabled, the script—the src compiled script, will not be cached.</li><li>• <b>Ignore acted on element being disabled.</b> Ignore the element acted on by a Vuser script function being disabled.</li></ul>

UI Element	Description
Timers	<ul style="list-style-type: none"><li>• <b>Optimize timers at end of step.</b> When possible, executes a setTimeout/setInterval/&lt;META refresh&gt; that expires at the end of the step before the expiration time</li></ul> <p><b>Default value:</b> Yes.</p> <ul style="list-style-type: none"><li>• <b>Single setTimeout/setInterval threshold (seconds).</b> Specifies an upper timeout for the window.setTimeout and window.setInterval methods. If the delay exceeds this timeout, these methods will not invoke the functions that are passed to them. This emulates a user waiting a specified time before clicking on the next element.</li></ul> <p><b>Default value:</b> 5 seconds.</p> <ul style="list-style-type: none"><li>• <b>Accumulative setTimeout/setInterval threshold (seconds).</b> Specifies a timeout for the window.setTimeout and window.setInterval methods. If the delay exceeds this timeout, additional calls to window.setTimeout and window.setInterval will be ignored. The timeout is accumulative per step.</li></ul> <p><b>Default value:</b> 30 seconds.</p> <ul style="list-style-type: none"><li>• <b>Reestablish setInterval at end of step.</b> 0 = No; 1 = Once; 2 = Yes.</li><li>• <b>Limit no-network timers at end of step:</b> Limit the number of setTimeout/setInterval specified script evaluations at the end of a step when no network requests are issued. Set to zero (0) for no limit. The default value is 100. This limit is only used when 'Optimize timers at end of step' is enabled.</li></ul>
History	<ul style="list-style-type: none"><li>• <b>History support.</b> Enables support for the window.history object for the test run. The options are <b>Enabled</b>, <b>Disabled</b>, and <b>Auto</b>. The <b>Auto</b> option instructs Vusers to support the window.history object only if it was used in the first iteration. Note that by disabling this option, you improve performance.</li></ul> <p><b>Default value:</b> auto.</p> <ul style="list-style-type: none"><li>• <b>Maximum history size.</b> The maximum number of steps to keep in the history list.</li></ul> <p><b>Default value:</b> 100 steps.</p>

UI Element	Description
Navigator Properties	<ul style="list-style-type: none"><li>• <b>navigator.browserLanguage.</b> The browser language set in the navigator DOM object's <b>browserLanguage</b> property. <b>Default value:</b> The recorded value. Scripts created with older recording engines use <b>en-us</b> by default.</li><li>• <b>navigator.systemLanguage.</b> The system language set in the navigator DOM object's <b>systemLanguage</b> property. <b>Default value:</b> The recorded value. Scripts created with older recording engines use <b>en-us</b> by default.</li><li>• <b>navigator.userLanguage.</b> The user language set in the navigator DOM object's <b>userLanguage</b> property. <b>Default value:</b> The recorded value. Scripts created with older recording engines use <b>en-us</b> by default.</li></ul>
Screen Properties	<ul style="list-style-type: none"><li>• <b>screen.width</b> Sets the width property of the screen DOM object in pixels. <b>Default value:</b> 1024 pixels.</li><li>• <b>screen.height</b> Sets the height property of the screen DOM object in pixels. <b>Default value:</b> 768 pixels.</li><li>• <b>screen.availWidth</b> Sets the availWidth property of the screen DOM object in pixels. <b>Default value:</b> 1024 pixels.</li><li>• <b>screen.availHeight</b>. Sets the availHeight property of the screen DOM object in pixels. <b>Default value:</b> 768 pixels.</li></ul>

UI Element	Description
Memory Management	<ul style="list-style-type: none"><li><b>Default block size for DOM memory allocations.</b> Sets the default block size for DOM memory allocations. If the value is too small, it may result in extra calls to malloc, slowing the execution times. Too large a block size, may result in an unnecessarily big footprint.  <b>Default value:</b> 16384 bytes.</li><li><b>Memory Manager for dynamically-created DOM objects.</b> <b>Yes</b>—Use the Memory Manager for dynamically-created DOM objects. <b>No</b>—Do not use the Memory Manager, for example when multiple DOM objects are dynamically created in the same document as under SAP. <b>Auto</b>—Use the protocol recommended (default Yes for all protocols except for SAP).</li><li><b>JavaScript Runtime memory size (KB).</b> Specifies the size of the JavaScript runtime memory in kilobytes.  <b>Default value:</b> 256 KB.</li><li><b>JavaScript Stack memory size (KB).</b> Specifies the size of the JavaScript stack memory in kilobytes.  <b>Default value:</b> 32 KB.</li></ul>
Web Javascript	<ul style="list-style-type: none"><li><b>Enable running Javascript code.</b> <b>Yes</b>—Enables running web Javascript steps, such as <code>web_js_run()</code> and <code>web_js_reset()</code>. <b>No</b>—Web Javascript steps can not be run. Note that enabling this option causes the creation of a Javascript Engine Runtime, even if there are no Javascript steps in the script.  <b>Default value:</b> No</li><li><b>Javascript Engine runtime size (KB).</b> Specifies the size of the Javascript Engine Runtime memory in kilobytes. One Runtime will be created for all Vusers in a process.  <b>Default value:</b> 10240 KB</li><li><b>Javascript Engine stack size per-thread (KB).</b> Specifies the size of each Vuser thread in the Javascript Engine memory, in kilobytes.  <b>Default value:</b> 32 KB</li></ul>

## ***Internet Protocol > Proxy Node***

Enables you to set the proxy server connection settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Internet Protocol &gt; Proxy</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>No proxy</b>	All Vusers should use direct connections to the Internet. This means that the connection is made without using a proxy server.
<b>Obtain the proxy settings from the default browser</b>	All Vusers use the proxy settings of the default browser from the machine upon which they are running. <b>Note:</b> This option is not available when Firefox has been set as the default browser. Uninstall Firefox and set another browser as default.
<b>Use custom proxy</b>	All Vusers use a custom proxy server. You can supply the actual proxy server details or the path of a proxy automatic configuration script (. pac file) that enables automatic configuration. <ul style="list-style-type: none"> <li>• <b>Use automatic configuration script.</b> Allows you to specify a JavaScript file containing proxy assignment information. This script tells the browser when to access a proxy server and when to connect directly to the site, depending on the URL. In addition, it can instruct the browser to use a specific proxy server for certain addresses and another server for other addresses. Specify the location of the script in the <b>Address</b> field.</li> <li>• Use proxy server. You can specify one proxy server for all <b>HTTP</b> sites, and another proxy server for all <b>HTTPS</b> (secure) sites or check the <b>use the same proxy server for all protocols</b> box.</li> <li>• <b>Exceptions ...</b>. Allows you to specify exceptions to the proxy server rules.</li> <li>• <b>Authentication ...</b>. Opens the Proxy Authentication Dialog Box. If the proxy server requires authentication for each Vuser, use this dialog box to enter the relevant password and user name. To add authentication dynamically during recording, or to add authentication for multiple proxy servers, use the <code>web_set_user</code> function. For more information, see the Function Reference ( Help &gt; Function Reference).</li> </ul>

## **Java Environment Settings > Java Classpath Node**

The **ClassPath** section lets you specify the location of additional classes that were not included in the system's classpath environment variable. You may need these classes to run Java applications

and insure proper replay.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Java Environment Settings &gt; Classpath</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
 Add	<b>Add Classpath.</b> Adds a new line to the classpath list. Use the <b>Browse</b> button to locate the classpath.  <b>Note:</b> Adding multiple JAR files at once is only supported if you have Internet Explorer 10 or higher.
 Delete	<b>Delete.</b> Permanently removes a classpath.
 Edit	<b>Edit Classpath.</b> Allows you to edit the path for the selected classpath.
<b>Classpath Entries List</b>	A list of classpath entries.

## **Java Environment Settings > Java VM Node**

Enables you to set the Java VM run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Java Environment Settings &gt; Java VM</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description

<b>Virtual Machine Settings</b>	<ul style="list-style-type: none"> <li><b>Use internal logic to locate JDK.</b> Search the PATH, registry, and Windows folder for the JDK to use during replay.</li> <li><b>Use specified JDK.</b> Use a specified JDK during replay.</li> <li><b>JDK.</b> The home folder of the specified JDK.</li> <li><b>Additional VM Parameters.</b> Any optional parameters used by the virtual machine.</li> <li><b>Using Xbootclasspath parameters.</b> Replays the script with the Xbootclasspath /p option.</li> </ul>
<b>Class Loading Settings</b>	<b>Load each Vuser using dedicated class loader.</b> Load each Vuser using a dedicated class loader. This will allow you to use a unique namespace for each Vuser and manage their resources separately.

## JMS > Advanced Node

Enables you to set the JMS Advanced run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; JMS &gt; Advanced</b>
<b>Important information</b>	This node is available only for the Web Service protocol. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.
<b>Relevant tasks</b>	<a href="#">"How to Prepare Scripts for Replay"</a> on page 894

User interface elements are described below:

### VM (Virtual Machine)

UI Element	Description
<b>Use external VM</b>	Enables you to select a VM (Virtual Machine) other than the standard one. If you disable this option, Vusers use the JVM provided with VuGen.
<b>JVM Home</b>	Location of the external JVM. This should point to the JDK home folder, defined by JDK_HOME. VuGen supports JDK 1.4 and above.
<b>Classpath</b>	Vendor implementation of JMS classes together with any other required supporting classes, as determined by the JMS implementation vendor.

## JMS

UI Element	Description
<b>Additional VM Parameters</b>	Extra parameters to send to the JVM such as Xbootclasspath, and any parameters specified by the JVM documentation.
<b>JNDI initial context factory</b>	The fully qualified class name of the factory class that will create an initial context. Select a context factory from the list or provide your own.
<b>JNDI provider URL</b>	URL string of the service provider. For example: <ul style="list-style-type: none"> <li>• Weblogic - t3://myserver:myport</li> <li>• Websphere - iiop://myserver:myport</li> </ul>
<b>JMS connection factory</b>	JNDI name of the JMS connection factory. You can only specify one connection factory per script.
<b>JMS security principal</b>	Identity of the principal (for example the user) for the authentication scheme.
<b>JMS security credentials</b>	The principal's credentials for the authentication scheme.
<b>Number of JMS connections per process</b>	The number of JMS connections per mdrv process, or Vuser. All Vusers sharing a connection will receive the same messages. The default is 1, and the maximum is 50 Vusers. The fewer connections you have per process, the better your performance.
<b>Received message timeout options</b>	The timeout for received messages: <ul style="list-style-type: none"> <li>• <b>Infinite wait.</b> Wait as long as required for the message before continuing.</li> <li>• <b>No wait.</b> Do not wait for the Receive message, and return control to the script immediately. If there was no message in the queue, the operation fails.</li> <li>• <b>Specify the timeout in seconds.</b> A timeout value for the message. If the timeout expired and no message has arrived, the operation fails. (default)</li> </ul> <p><b>User defined timeout.</b> The amount of seconds to wait for the message before timing out. The default is twenty seconds.</p> <ul style="list-style-type: none"> <li>• <b>Default value:</b> No wait.</li> </ul>
<b>Automatically generate selector</b>	Generates a selector for the response message with the correlation ID of the request ( <b>No</b> by default). Each JMS message sent to the server has a specific ID. Enable this option if you want VuGen to automatically create a selector that includes the message ID.

## MMS > Server and Protocol Node

Enables you to set the MMS (Multimedia Messaging Service) run-time settings.

To access	VuGen > Replay > Run-Time Settings > MMS > Server and Protocol
<b>Important information</b>	<ul style="list-style-type: none"><li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 320</a>.</li><li>In the <b>General &gt; Miscellaneous node</b>, under Multithreading, select <b>Run Vuser as a process</b>.</li></ul>

User interface elements are described below:

UI Element	Description
<b>Automatic WAP Connections</b>	Defines when to connect and disconnect from a WAP gateway. This setting is only relevant when a WAP gateway is used. The possible values are: <b>Per Iteration.</b> Connect at the beginning of each iteration and disconnect at the end of each iteration. <b>Per Send or Receive.</b> Connect and disconnect at the beginning and end of each message. <b>None.</b> Do not use automatic WAP connections. <b>Default value:</b> Per Iteration.
<b>Default Sender address</b>	The default address sent in the Sender header. <b>Default value:</b> +999999.
<b>MMS Version</b>	The version of the MMS protocol used by the script.
<b>MMSC URL</b>	The URL of the MMSC (Multimedia Messaging Center) server.
<b>SMSC IP</b>	The IP address of the SMSC server used for sending MMS notifications over SMPP.
<b>SMSC Port</b>	The IP port of the SMSC server used for sending MMS notifications over SMPP.
<b>Timeout (seconds)</b>	The time that the server waits for incoming messages. <b>Default value:</b> 60 seconds.

## Mobile TruClient Properties > Mobile Device Node

This pane enables you to select a mobile device properties when recording a TruClient Ajax - Mobile script.

<b>To access</b>	<ul style="list-style-type: none"><li>• VuGen &gt; Replay &gt; Run-Time Settings &gt; Mobile TruClient Properties &gt; Mobile Device Node</li><li>• Select <b>Mobile Device</b> button from the Main VuGen Toolbar</li></ul> 
<b>Relevant tasks</b>	<p>"How to Add, Remove, and Import Mobile Device Settings for Mobile TruClient" on page 716</p> <p>"How to Record a Script with Mobile TruClient" on page 715</p>

User interface elements are described below:

UI Element	Description
<b>Mobile Device</b>	Select the mobile device type you want to test.
<b>User Agent</b>	Specify the header string that is sent to server to identify your mobile device. Once you have selected a device, the default header value will appear. However, this header string can be modified.
<b>Display</b>	Specify the height and width of your mobile device screen. Mobile TruClient will open browser window according to the display settings.

## .NET > .NET Environment Node

Enables you to set the run-time settings for .NET Vuser scripts.

<b>To access</b>	VuGen > Replay > Run-Time Settings > .NET > .NET Environment
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "Protocol Compatibility Table" on page 320.

User interface elements are described below:

UI Element	Description

<b>AUT configuration</b>	Configuration settings for the AUT location and configuration files. <ul style="list-style-type: none"> <li><b>AUT Application Base Path.</b> The AUT (Application Under Test) base folder from which DLLs are loaded during replay. By default, during recording, all of the necessary DLLs are stored in the script's folder. Use this option to specify the location of any missing DLL files for the AUT. This is usually the installation path of the recorded application. Note that the AUT must be installed on the machine running the script. If you leave this box empty, VuGen uses the local script\bin folder as the application base folder during replay.</li> <li><b>AUT Configuration File.</b> The file name of the recorded application's configuration file. VuGen copies the AUT configuration file to the <b>script\bin</b> folder and loads the locally saved file. To specify a different location, enter a full path. If you only specify a file name, and the file is not in the <b>script\bin</b> folder, VuGen loads it from the App base folder.</li> </ul>
<b>Concurrency</b>	<b>AppDomain Per Vuser.</b> Enables execution of each Vuser in a separate app domain. Running Vusers in separate App Domains enables each Vuser to execute separately without sharing static variables and prevents locking between them. <b>Default value:</b> true.

## .NET > Shared DLLs

This dialog box enables you to view and modify the list of shared DLLs after you record a Vuser script. If a DLL is included in the list of shared DLLs, when the Vuser script is run and requires a particular DLL, the Vuser will access the DLL in its shared location – the DLL will not be copied to the load generator. Adding a DLL to the list of shared DLLs therefore saves hard-drive space on the load generator when a Vuser is run.

**Note:** The Use Shared DLLs option is accessible from both the Recording Options and Run-time Settings. If you use modify the list or DLL folder from the Run-time Settings via the Controller, the changes will be ineffective.

**Workaround:** Modify the DLL list through VuGen and not through the Controller.

After you record a Vuser script, the list of shared DLLs is copied from the Recording Options to the Run-Time Settings. For details on how to view and modify the recording options, see "[".NET > Shared DLLs" on page 224](#).

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Microsoft .NET &gt; Shared DLLs</b>
<b>See also</b>	<a href="#">".NET &gt; Shared DLLs" on page 224</a>

User interface elements are described below:

UI Element	Description
 Add	<b>Add.</b> Adds a new line to the DLL Entries list. Specify a full path to the DLL.  <b>Note:</b> The location that you specify for a shared DLL, must be accessible to <i>all</i> load generators on which the Vuser will run.
 Edit	<b>Edit.</b> Allows you to edit the path to the selected DLL.
 Delete	<b>Delete.</b> Permanently removes the DLL entry.
DLL Entries List	A list of classpath entries.

## Network > Speed Simulation Node

Enables you to configure the network speed run-time settings.

To access	VuGen > Replay > Run-Time Settings > Network > Speed Simulation
Important information	<ul style="list-style-type: none"><li>This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see "<a href="#">Protocol Compatibility Table</a>" on <a href="#">page 320</a>.</li><li>On Linux machines, this setting is only supported for the Web (HTTP/HTML) protocol.</li></ul>

User interface elements are described below:

UI Element	Description
Use bandwidth	Indicate a specific bandwidth level for your Vuser to emulate. You can select a speed ranging from 14.4 to 512 Kbps, emulating analog modems, ISDN, or DSL.
Use custom bandwidth	Indicate a bandwidth limit for your Vuser to emulate. Specify the bandwidth in bits, where 1 Kilobit=1024 bits.
Use maximum bandwidth	Vusers run at the maximum bandwidth that is available over the network. <b>Default value:</b> enabled.

## Oracle NCA > Client Emulation Node

Enables you to set the Oracle NCA run-time settings.

To access	VuGen > Replay > Run-Time Settings > Oracle NCA > Client Emulation
-----------	--

<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.
------------------------------	--

User interface elements are described below:

UI Element	Description
<b>Network</b>	<ul style="list-style-type: none"><li>• <b>Socket Mode.</b> Configure the connection between the client and server at the socket level.<ul style="list-style-type: none"><li>▪ <b>Timeout.</b> The time that an Oracle NCA Vuser waits for a response from the server. <b>Default value:</b> -1 (disables the timeout and the client waits indefinitely).</li><li>• <b>Pragma Mode.</b> Configure the communication on the Oracle-defined Pragma mode (higher level than socket and HTTP).</li><li>▪ <b>Max Retries.</b> The maximum number of <b>IfError</b> messages the client will accept from the server before issuing an error. <b>IfError</b> messages are the periodic messages the server sends to the client, indicating that it will respond with the data as soon as it is able.</li><li>▪ <b>Retry Interval (ms).</b> The interval (in milliseconds) between retries in the case of <b>IfError</b> messages.</li><li>▪ <b>Include retry intervals in transaction.</b> Includes the interval between retry time, as part of the transaction duration time.</li></ul></li><li>• <b>Enable Heartbeat.</b> Sends a heartbeat signal is sent to the server. You can configure the frequency of the heartbeat by setting the <b>frequency</b> property. <b>Default value:</b> enabled, 120.</li></ul>
<b>Connection</b>	<ul style="list-style-type: none"><li>• <b>Forms version.</b> The version of the Oracle Forms server detected during recording. Modify this setting only if the server was upgraded since the recording.</li><li>• <b>Command line parameter separator.</b> Marker for the division between separate parameters in a command line string.</li></ul>
<b>Diagnostic</b>	<ul style="list-style-type: none"><li>• <b>Application Version.</b> The version of Oracle Application. This option is relevant when using Oracle Application—not a custom Oracle NCA application. It is only required when using Oracle database breakdown.</li></ul>

## RDP > Advanced Node

Enables you to set the RDP advanced run-time settings.

To access	VuGen > Replay > Run-Time Settings > RDP > Advanced
-----------	---

<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.
------------------------------	--

User interface elements are described below:

UI Element	Description
<b>Bitmap caching</b>	Allows the remote desktop server to use bitmap caching. Enabling this setting can save system resources on the remote desktop server.
<b>Font smoothing</b>	Allows the remote desktop server to use font smoothing. Disabling this setting can save system resources on the remote desktop server.
<b>Menu and window animation</b>	Allows the remote desktop server to animate menus and windows. Disabling this setting can save system resources on the remote desktop server.
<b>Remote desktop composition</b>	Enables remote desktop composition.
<b>Show contents of window while dragging</b>	Shows the contents of windows while they are being dragged. Disabling this setting can save system resources on the remote desktop server.
<b>Show remote desktop background image</b>	Allows you to run the remote desktop application without displaying the desktop background image on the remote desktop. Disabling this setting can save system resources on the remote desktop server.
<b>Socket receive buffer size (bytes)</b>	The number of bytes to allocate for the socket's receive buffer. If the buffer is too small, it can fill up causing the server to disconnect. If the buffer is too large, it uses more local system resources (memory).
<b>Themes</b>	Allows the remote desktop server to use Windows themes. Disabling this setting can save system resources on the remote desktop server.

## RDP > Configuration Node

Enables you to set the RDP configuration run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; RDP &gt; Configuration</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Enable RDP caching</b>	Support data caching orders in RDP (enabled by default).
<b>RDP Client Version Emulation</b>	The version of RDP packets to produce during replay: <b>As Recorded</b> , or a specific version number.
<b>Remote desktop color depth</b>	The color depth settings for the replay: <b>As Recorded</b> , or a specific depth.
<b>Remote desktop resolution (pixels)</b>	The size of the window in which the applications are run: <b>As Recorded</b> , or a specific size (in pixels).
<b>Start the following program on connection</b>	Open RDP connection to invoke the specified application. Specify the following information: <b>Program path and file name</b> and optionally, <b>Start in folder</b> .
<b>Supported Protocols</b>	<p>Specify the type of authentication that is used by the Vuser to connect to the server when the script is replayed:</p> <ul style="list-style-type: none"> <li><b>RDP</b>: Connects without employing any authentication.</li> <li><b>CredSSP</b>: Connects using the Credential Security Support Provider (CredSSP) protocol to perform strong server authentication.</li> <li><b>SSL</b>: Enables clients to authenticate to servers and provides a secure channel by encrypting communications.</li> </ul>

## RDP > RDP Agent Node

Enables you to set the RDP Agent run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; RDP &gt; RDP Agent</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Replay using RDP agent</b>	<p>Instructs VuGen to use the extended information gathered by the RDP agent during recording. This requires you to have recorded the session with the <b>Use RDP agent</b> Recording Option enabled. The LoadRunner RDP agent must be installed on the server. For details, see "<a href="#">How to Install / Uninstall the RDP Agent</a>" on page 755.</p> <p><b>Wait time for RDP agent response.</b> The maximum time in milliseconds to wait for the agent to respond to a request.</p>

UI Element	Description
Enable RDP agent log	<p>Enables the RDP agent log. This feature should be used only for debugging purposes.</p> <ul style="list-style-type: none"> <li>• <b>RDP agent log detail level.</b> Configures the level of detail generated in the RDP agent log with <b>Standard</b> being the lowest level of detail and <b>Extended Debug</b> being the highest level of detail.</li> <li>• <b>RDP agent log destination.</b> Configures the destination of the RDP agent log data. <b>File</b> saves the log messages only on the remote server side. <b>Stream</b> sends the log messages to the VuGen machine. <b>FileAndStream</b> sends the log messages to both destinations.</li> <li>• <b>RDP agent log folder.</b> The folder path on the remote server that the RDP agent log file will be generated in. If none is specified and the agent log destination was set to <b>File</b>, the log is saved in the temp folder of the user on the server.</li> </ul>

## RDP > Synchronization Node

Enables you to set the RDP synchronization run-time settings.

To access	VuGen > Replay > Run-Time Settings > RDP > Synchronization
Important information	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
Default input origin	The default origin for input operations.
Default offset addition	Saves the offset of images that moved during synchronization for all subsequent functions. <b>Default value:</b> No.
Default synchronization timeout (sec)	The time in seconds to wait for synchronization operations. Enter a value between 0 and 1000. <b>Default value:</b> 60.

<b>Default tolerance for image synchronization</b>	The tolerance level for performing synchronization on images. Select one of the options: <b>Exact</b> , <b>Low</b> , <b>Medium</b> , or <b>High</b> . <b>High</b> has the most tolerance for changes and mismatches. <b>Low</b> requires a match of approximately 95 percent, <b>Medium</b> requires a match of approximately 85 percent, <b>High</b> requires a match of approximately 70 percent, and <b>Exact</b> requires an 100 percent match. <b>Default value:</b> Medium.
<b>Disable synchronization failure dialog</b>	When selected, it prevents the Synchronization Failure Dialog box from opening. <b>Default value:</b> not selected.
<b>Fail image synchronization step on timeout</b>	Instructs Vusers how to proceed when images are not found during synchronization. <b>Yes</b> sets a Fail status and Vusers follow the Continue on Error setting. <b>No</b> returns an LR_NOT_FOUND flag, the step reports a warning and the script continues. <b>Default value:</b> Yes.
<b>Recorded</b>	Uses coordinates for all input operations with a non-specified input origin. <b>Default value:</b> enabled.
<b>Synched</b>	Adds the most recent offsets saved at one of the previous synchronization functions to the recorded coordinates of each input operation with a non-specified input origin.
<b>Typing speed (msec/char)</b>	The time in milliseconds for sending consecutive characters in keyboard commands. Enter a value between 0 and 1000. <b>Default value:</b> 150.

## RTE > RTE Node

Enables you to set the RTE run-time settings.

<b>To access</b>	VuGen > Replay > Run-Time Settings > RTE > RTE
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see <a href="#">"Protocol Compatibility Table" on page 320</a> .

User interface elements are described below:

UI Element	Description
<b>Maximum number of connection attempts</b>	The TE_connect function is generated by VuGen when you record a connection to a host. When you replay an RTE Vuser script, the TE_connect function connects the terminal emulator to the specified host. If the first attempt to connect is not successful, the Vuser retries a number of times to connect successfully. <b>Default value:</b> 5.

<b>Use original device name</b>	In certain environments, each session (Vuser) requires a unique device name. The TE_connect function generates a unique 8-character device name for each Vuser, and connects using this name. Select this option to connect using the device name that is contained within the com_string parameter of the TE_connect function. <b>Note:</b> The original device name setting applies to IBM block-mode terminals only.
<b>Delay before typing</b>	The delay setting determines how Vusers execute <b>TE_type</b> functions. <ul style="list-style-type: none"> <li><b>First key.</b> Specify the amount of time (in milliseconds) that a Vuser waits before entering the first character in a string.</li> <li><b>Subsequent keys.</b> Specifies the amount of time (milliseconds) that a Vuser waits before between submitting successive characters.</li> </ul> <b>Note:</b> You can use the <b>TE_typing_style</b> function to override the Delay settings for a portion of a Vuser script.
<b>X-System synchronization</b>	<ul style="list-style-type: none"> <li><b>Timeout.</b> The timeout (in seconds) to wait for the system to stabilize when replaying a <b>TE_wait_sync</b> function before an error is returned.</li> <li><b>Stable time.</b> The time (in milliseconds) that the Vuser waits to ensure that the terminal is no longer in the X-SYSTEM mode after executing a <b>TE_wait_sync</b> function.</li> </ul>

## SAPGUI > General Node

Enables you to set the SAP GUI run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; SAPGUI &gt; General</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Send status bar text</b>	Send the text from the status bar to the log file.
<b>Send active window title</b>	Send the active window title text to the log file.

<b>Show SAP Client during replay</b>	Shows an animation of the actions in the SAP client during replay. The benefit of displaying the user interface (UI) is that you can see how the forms are filled out and closely follow the actions of the Vuser. This option, however, requires additional resources and may affect the performance of your load test. <ul style="list-style-type: none"> <li><b>Take ActiveScreen snapshots during replay.</b> Captures replay snapshots with the Control ID information for all active objects. ActiveScreen snapshots differ from regular ones, in that they allow you to see which objects were recognized by VuGen in the SAP GUI client. As you move your mouse across the snapshot, VuGen highlights the detected objects. You can then add new steps to the script directly from within the snapshot. It also allows you to add steps interactively from within the snapshot for a specific object. For more information, see "<a href="#">How to Enhance SAP GUI Scripts</a>" on page 790.</li> </ul>
<b>Options...</b>	Opens the SAP GUI Advanced Options Dialog Box, enabling you to set the following settings: <ul style="list-style-type: none"> <li><b>Replay using running SAPlogon application.</b> Instructs the Vusers to use the SAPlogon application that is currently running for replay.</li> <li><b>Set SAPfewgsvr application timeout.</b> Allows you to modify the <b>SAPfewgsvr.exe</b> process timeout.</li> <li><b>Timeout to SAPfewgsvr.</b> The SAPfewgsvr.exe process timeout in seconds. <b>Default value:</b> 300 seconds.</li> </ul>

## Silverlight > Services Node

Displays the WSDL files associated with your script and allows you to modify their settings for the replay phase.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; Silverlight &gt; Services</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>&lt;Service List&gt;</b>	A list of the WSDL files that are available for this script.
<b>Protocol =; Security Data</b>	Opens the Protocol and Security Scenario Data dialog box, allowing you to configure a number of settings for each selected WSDL. For more information, see " <a href="#">Protocol and Security Scenario Data Dialog Box</a> " on page 242.

## WAP > Gateway Node

Enables you to set the WAP gateway run-time settings.

<b>To access</b>	VuGen > Replay > Run-Time Settings > WAP > Gateway
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>HTTP Direct</b>	Run the Vusers run in HTTP mode, accessing a Web server directly.
<b>WAP Gateway Property</b>	Run the Vusers accessing a Web server via a WAP Gateway. <ul style="list-style-type: none"><li>• <b>IP.</b> The IP of the gateway.</li><li>• <b>Port.</b> The port of the gateway. When running your Vusers through a WAP gateway, VuGen automatically sets default port numbers, depending on the selected mode. However, you can customize the settings and specify a custom IP address and port for the gateway.</li><li>• <b>WAP 1.x (WSP).</b> Selects the appropriate WAP version. If you recorded in WAP 1.x (WSP), you can run the Vuser in either 1.x (WSP), or 2.0 (HTTP proxy) mode. If you select this option, you can set the WAP 1.x (WSP) Properties. For more information, see "<a href="#">WAP 1.x (WSP) Properties</a>" below.</li><li>• <b>WAP 2.0 (HTTP).</b> Selects the appropriate WAP version. If you recorded in WAP 2.0 (HTTP proxy), then you can only run the Vuser in the same mode.</li></ul>

### WAP 1.x (WSP) Properties

UI Element	Description
<b>Advanced</b>	Expand to set the Advanced Properties. For more information see " <a href="#">Advanced Properties</a> " on the next page.
<b>Connection Options</b>	<ul style="list-style-type: none"><li>• <b>Connection-oriented Mode</b> sets the connection mode for the WSP session to Connection-Oriented.</li><li>• <b>Connectionless Mode</b> sets the connection mode for the WSP session to Connectionless.</li></ul>
<b>Enable Security</b>	Enable a secure connection to the WAP gateway.

### Advanced Properties

UI Element	Description
<b>Acknowledge headers</b>	Returns standard headers that provide information to the gateway. <b>Default value:</b> Disabled.
<b>BearerType</b>	The type of bearer used as the underlying transport.
<b>CAPSessionResume</b>	Enables requests for session suspend or resume.
<b>Client SDU buffer size</b>	The largest transaction service data unit that may be sent to the client during the session. <b>Default value:</b> 4000.
<b>Confirm Push support</b>	In CO mode, if a push message is received, this option instructs the Vuser to confirm the receipt of the message. For more information, see VuGen Push Support.
<b>MethodMOR</b>	The number of outstanding methods that can occur simultaneously.
<b>Network MTU Size</b>	The maximum size in bytes, of the network packet. <b>Default value:</b> 4096.
<b>Push support</b>	Enables push type messages across the gateway. <b>Default value:</b> Disabled.
<b>PushMOR</b>	The number of outstanding push transactions that can occur simultaneously.
<b>Retrieve messages</b>	When a push messages is received, this option instructs the Vuser to retrieve the message data from the URL indicated in the push message. <b>Default value:</b> Disabled.
<b>Server SDU buffer size</b>	The largest transaction service data unit that may be sent to the server during the session. <b>Default value:</b> 4000.
<b>Support Cookies</b>	Provide support for saving and retrieving cookies. <b>Default value:</b> Disabled.
<b>WTLS Abbreviated Handshake</b>	Use an abbreviated handshake instead of a full one, when receiving a redirect message. <b>Default value:</b> False.
<b>WTLS Diffie Hellman</b>	Use the Diffie Hellman encryption scheme for WTLS (Wireless Transport Layer Security) instead of the default scheme, RSA. <b>Default value:</b> False.
<b>WTLS Diffie Hellman identifier</b>	An identifier for the Diffie Hellman encryption scheme. This identifier is required for the abbreviated handshake with the Operwave gateway that uses the Diffie Hellman encryption scheme.

UI Element	Description
<b>WTP Retransmission Time</b>	The time in seconds that the WTP layer waits before re-sending the PDU if it did not receive a response. <b>Default value:</b> 5000.
<b>WTP Segmentation and Reassembly</b>	Enables segmentation and reassembly (SAR) in WTP, Wireless Transport Protocol. <b>Default value:</b> True.

## ***WAP > Radius Node***

Enables you to set the WAP radius run-time settings.

<b>To access</b>	<b>VuGen &gt; Replay &gt; Run-Time Settings &gt; WAP &gt; Radius</b>
<b>Important information</b>	This node is available only for specific protocols. For a complete list of protocols and their associated nodes, see " <a href="#">Protocol Compatibility Table</a> " on page 320.

User interface elements are described below:

UI Element	Description
<b>Accounting port number</b>	Accounting port of the Radius server.
<b>Authentication port number</b>	Authentication port of the Radius server.
<b>Connection Timeout (sec)</b>	The time in seconds to wait for the Radius server to respond. <b>Default value:</b> 120 seconds.
<b>IP Address</b>	IP address of the Radius server.
<b>Network Type</b>	Accounting network type: GPRS (General Packet Radio Service) or CSD (Circuit-Switched Data).
<b>Radius client IP</b>	Radius packets source IP, usually used to differentiate between packets transmitted on different NIC cards on a single Load Generator machine.
<b>Retransmission retries</b>	The number of times to retry after a failed transmission. <b>Default value:</b> 0.
<b>Secret Key</b>	The secret key of the Radius server.
<b>Store attributes returned by the server to parameters</b>	Allow Vusers to save attributes returned by the server as parameters, which can be used at a later time. <b>Default value:</b> False.

## Bookmarks Overview

When you edit a Vuser script, you can use bookmarks to navigate between sections of the script. When you add a bookmark, a bookmark icon is added to the left of the selected line in your script.

The Bookmarks pane displays a list of all bookmarks that exist in the Vuser script. Using the Bookmarks pane, you can:

- Navigate to the location of the bookmark in your script.
- Navigate between consecutive bookmarks in the pane.
- Delete an individual bookmark.
- Clear all bookmarks.

For task details, see ["How to Use Bookmarks" on page 385](#).

## How to Run a Vuser Script from a Command Prompt

This task describes how to run a Vuser script from a command prompt or from the Windows Run dialog box—without the VuGen user interface.

To send command line parameters to a Vuser from within VuGen, add the attributes and their values in the Run-Time settings dialog box. For details, see the ["General > Additional Attributes Node" on page 335](#).

To run a script from a command line or the Run dialog box:

1. Open a **Command Prompt** window, or select **Start > Run** to open the Run dialog box.

2. Type **mdrv** followed by the script name, using the following syntax:

```
<installation_dir>/bin/mdrv.exe -usr <script_name>
```

where **script\_name** is the full path to the *.usr* script file, for example,  
**c:\temp\mytest\mytest.usr**.

3. Add other command line options and arguments.

4. Click **Enter**. The **mdrv** program runs a single instance of the script without the user interface. The output files provide the run-time information.

For a complete list of the command line options, type **mdrv** at a command prompt from the LoadRunner **bin** folder, without any arguments. The following examples provide common usages of a command line expression:

- You can specify the load generator, as well as indicate the number of times to run the script as indicated by the following example:

```
script1 -host pc4 -loop 5
```

- Specify a location for the output files. For example:

```
-out c:\tmp\vuser
```

- Specify arguments to pass to your script by using the following format:

```
script_name -arg_name arg_value -arg_name arg_value
```

You can retrieve the command line values by parsing the command line during replay, using the parsing functions, such as **Ir\_get\_attrib\_double**. For details, see the Function Reference (**Help > Function Reference**).

**Note:** The Linux command line utility, *run\_db\_vuser*, does not yet support many of the standard Windows command line options. For details, see Running a Vuser from the Linux Command Line.

## How to Run a Vuser Script from a Linux Command Line

When using VuGen to develop Linux-based Vusers, you must check that the recorded script runs on the Linux platform. This task describes how to perform this check and run a Vuser script from a Linux command.

### 1. Verify that the script replays in VuGen

Replay the script in VuGen to verify that the script works in windows before attempting to run it in Linux. This is recommended because it is easier to edit and debug the script in VuGen. For task details, see "[How to Replay a Vuser Script](#)" on page 316.

### 2. Copy the script files to the Linux server

Transfer the script files to the Linux server

### 3. Check the Vuser setup on the Linux machine by using verify\_generator.

If you intend to run all of the Vusers on one host, type:

```
verify_generator
```

The verify\_generator either returns **OK** when the setting is correct, or **Failed** and a suggestion on how to correct the setup.

For detailed information about the verify checks type:

```
verify_generator [-v]
```

The verify utility checks the local host for its communication parameters and its compatibility with all types of Vusers. It checks the following items in the Vuser environment:

- at least 128 file descriptors
- proper **.rhost** permissions: **-rw-r--r--**
- the host can be contacted using rsh to the host. If not, checks for the host name in **.rhosts**
- **M\_LROOT** is defined
- **.cshrc** defines the correct **M\_LROOT**
- **.cshrc** exists in the home directory
- the current user is the owner of the **.cshrc**
- a LoadRunner installation exists in **\$M\_LROOT**
- the executables have executable permissions
- **PATH** contains **\$M\_LROOT/bin**, and **/usr/bin**
- the **rstatd** daemon exists and is running

#### 4. Run the script

Run the script in standalone mode from the Vuser script folder, using the **run\_db\_vuser** shell script:

```
run_db_vuser.sh <commands> script_name.usr
```

The *run\_db\_vuser* shell script has the following command line options:

Command	Description
<b>--help</b>	Display the available options. (This option must be preceded by two dashes.)
<b>-cpp_only</b>	Run cpp only (pre-processing) on the script.
<b>-cci_only</b>	Run cci only (pre-compiling) on the script to create a file with a .ci extension. You can run cci only after a successful cpp.
<b>-driver</b> <b>driver_path</b>	Use a specific driver program. Each database has its own driver program located in the /bin folder. For example, the driver for <b>CtLib</b> located in the /bin folder, is <b>mdrv</b> . This option lets you specify an external driver.

<b>-exec_only</b>	Execute the Vuser .ci file. This option is available only when a valid .ci file exists.
<b>-ci ci_file_name</b>	Execute a specific .ci file.
<b>-out output_path</b>	Place the results in a specific folder.

By default, `run_db_vuser.sh` runs **cpp**, **cci**, and **execute** in verbose mode. It uses the driver in the VuGen installation\bin folder, and saves the results to an output file in the Vuser script folder. You must always specify a `.usr` file. If you are not in the script folder, specify the full path of the `.usr` file.

For example, the following command line executes a Vuser script called test1, and places the output file in a folder called results1. The results folder must be an existing folder—it will not be created automatically:

```
run_db_vuser.sh-out /u/joe/results1 test1.usr
```

## How to Use Bookmarks

When working in the Editor, VuGen lets you place bookmarks at various locations within your script. You can navigate between the bookmarks to analyze and debug your code. The following steps describe how to work with bookmarks. Most of the bookmark functionality is available from VuGen's Bookmarks pane. To access the Bookmarks pane, click **View > Bookmarks**.

### Create a Bookmark

In the Editor, place the cursor at the desired location and press Ctrl + F2. VuGen places a bookmark icon  in the left margin of the script.

### Remove a Bookmark

To remove a bookmark, perform one of the following:

- In the Editor, click in the line that contains the bookmark and press Ctrl + F2.
- In the Bookmark pane, select the bookmark that you want to delete and click the **Delete Bookmark** button .

VuGen removes the bookmark icon from the left margin.

### Navigate between Bookmarks

Click **View > Bookmarks** to display the Bookmarks pane.

- To move to the next bookmark, click the **Next Bookmark** button  or press **F2**.
- To return to the previous bookmark, click the **Previous Bookmark** button  or press **Shift + F2**.

You can navigate between bookmarks in the current action only. To navigate to a bookmark in another action, select that action in the left pane and then press F2.

### Navigate to a Specific Bookmark in a Vuser Script

In the Bookmarks pane, double-click the specific bookmark to which you want to navigate. The cursor flashes in the Editor at the start of the line containing the bookmark.

## Files Generated During Replay

This section describes what occurs when a Vuser script is replayed, and describes the files that are created.

1. The **options.txt** file is created. This file includes command line parameters to the preprocessor.

### Example of options.txt file

```
-DCCI
-D_IDA_XL
-DWINNT
-Ic:\tmp\Vuser           (name and location of Vuser include file
s)
-IE:\LRUN45B2\include     (name and location of include files)
-ec:\tmp\Vuser\logfile.log (name and location of output logfile)
  c:\tmp\Vuser\VUSER.c    (name and location of file to be processe
d)
```

2. The file **Vuser.c** is created. This file contains 'includes' to all the relevant .c and .h files.

### Example of Vuser.c file

```
#include "E:\LRUN45B2\include\lrun.h"
#include "c:\tmp\web\init.c"
#include "c:\tmp\web\run.c"
#include "c:\tmp\web\end.c"
```

3. The c preprocessor **cpp.exe** is invoked in order to 'fill in' any macro definitions, precompiler directives, and so on, from the development files.

The following command line is used:

```
cpp -foptions.txt
```

4. The file **pre\_cci.c** is created which is also a C file (**pre\_cci.c** is defined in the **options.txt** file). The file **logfile.log** (also defined in **options.txt**) is created containing any output of this process. This file should be empty if there are no problems with the preprocessing stage. If the file is not empty then it is almost certain that the next stage of compilation will fail due to a fatal error.
5. The **cci.exe** C compiler is now invoked to create a platform-dependent pseudo-binary file (.ci) to be used by the Vuser driver program that will interpret it at run-time. The cci takes the **pre\_cci.c** file as input.
6. The file **pre\_cci.ci** is created as follows:

```
cci -errout c:\tmp\Vuser\logfile.log -c pre_cci.
```

7. The file **logfile.log** is the log file containing output of the compilation.
8. The file **pre\_cci.ci** is now renamed to **Vuser.ci**.

Since the compilation can contain both warnings and errors, and since the driver does not know the results of this process, the driver first checks if there are entries in the **logfile.log** file. If there are, it then checks if the file **Vuser.ci** has been built. If the file size is not zero, it means that the cci has succeeded to compile - if not, then the compilation has failed and an error message will be given.

9. The relevant driver is now run, taking both the **.usr** file and the **Vuser.ci** file as input. For example:

```
mdrv.exe -usr c:\tmp\Vuser\usr -out c:\tmp\Vuser -file c:\tmp\Vuser\Vuser.ci
```

The **.usr** file is needed since it tells the driver program which database is being used. This determines which libraries need to be loaded for the run.

10. If there is an existing replay log file, **output.txt**, (see the following entry), the log file is copied to **output.bak**.
11. The **output.txt** file is created (in the path defined by the 'out' variable). This file contains the output messages that were generated during the script replay. These are the same messages that appear in the Replay view of VuGen's Output pane.

## Debugging Vuser Scripts

The **Debugging** section describes the various methods that are available to debug Vuser scripts.

## Debugging - Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the fifth step, debugging a Vuser script.



After creating a Vuser script, replay the script to verify that the script runs without errors. Using VuGen's debug features, you can identify and resolve errors in your scripts. You can access most of these script debugging features from the VuGen toolbar.

### Running a Vuser script

To run a Vuser script until the end of the script or until the next breakpoint, perform one of the following:

- Select **Replay > Run**.
- Click the **Run** button  on the VuGen toolbar.
- Press **F5**.

**Note:** The status of the Vuser script execution appears in the lower left corner of VuGen. The script execution status may be **Ready**, **Running**, or **Paused**.

- To stop a script that is running, click the **Stop Replay**  button on the VuGen toolbar.
- To pause a script that is running, click the **Pause**  button on the VuGen toolbar.
- To continue running a script that is paused, click the **Continue**  button on the VuGen toolbar.

### The Run Step by Step Command

The **Run Step by Step** command runs the script one line at a time. This enables you to follow the script execution. The **Run Step by Step** command starts the script replay, and then pauses it on the first line of the script, usually in the `vuser_init()` action.

To run the script step by step, perform one of the following:

- Select **Replay > Run Step by Step**.
- Click the **Run Step by Step** button  on the VuGen toolbar.
- Press **F10**.

Note that the **Run Step by Step** button is available only while a script is being replayed.

## Animated Run

You can run a Vuser script in animated mode or non-animated mode. When you run in animated mode, VuGen highlights the line that is running in the Vuser script. When you run in non-animated mode, VuGen executes the Vuser script, but does not indicate the line being executed.

To toggle between the animated mode and the non-animated mode:

- Click the **Animated Run**  button on the VuGen toolbar.
- Click **Replay > Animated Run**.

Note that the **Animated Run** button is available only while a script is being replayed.

For details on how to set the run mode using VuGen options, see ["Scripting Options" on page 103](#).

## Breakpoints

Breakpoints pause script execution at specified points in the script. This enables you to examine the effects of the script on your application at pre-determined points during script execution.

- For concept details on breakpoints, see ["Working with Breakpoints" on page 392](#).
- For task details, see ["How to Debug Scripts with Breakpoints" on page 394](#).

## Bookmarks

When working in Script view, VuGen lets you place bookmarks at various locations within your script. You can navigate between the bookmarks to help analyze and debug your code.

- For task details, see ["How to Use Bookmarks" on page 385](#).

## Watching Variables

The Watch pane enables you to monitor variables and expressions while a script runs. You can monitor variables and expressions only when execution of a Vuser script is in the Paused state. To display the Watch pane, click **View > Debug > Watch**. For details on using the Watch pane, see ["Watching Expressions and Variables" on page 392](#).

## Go To Commands

- To navigate around a script using breakpoints, you can use the **Go To Source** command. For details, see ["How to Debug Scripts with Breakpoints" on page 394](#).
- To navigate around a script using bookmarks, you can use the **Next Bookmark** and **Previous Bookmark** commands. For details, see ["How to Use Bookmarks" on page 385](#).

If you want to examine the Replay log messages for a specific step or function, right-click the step in the Editor and select **Go To Step in Replay Log**. VuGen places the cursor at the start of the corresponding step in the Output pane's Replay log.

## Output Pane

The Output pane displays messages that were generated during the replay of your script. For details, see "[Output Pane](#)" on page 124.

To enable some recorded Vuser scripts to replay correctly, it may be necessary to implement correlation. Correlation is used when a recorded script includes a dynamic value (such as a session ID) and therefore cannot be successfully replayed. To resolve this, you convert the dynamic value into a variable—thereby enabling your script to replay successfully. For details, see "[Correlation Overview](#)" on page 274.

## Error Handling

You can specify how a Vuser handles errors during script execution. By default, when a Vuser detects an error, the Vuser stops executing the script. You can instruct a Vuser to continue with the next iteration when an error occurs using one of the following methods:

- Using run-time settings. You can specify the **Continue on Error** run-time setting. The **Continue on Error** run-time setting applies to the entire Vuser script. You can use the **Ir\_continue\_on\_error** function to override the **Continue on Error** run-time setting for a portion of a script.
- Using the **Ir\_continue\_on\_error** function. The **Ir\_continue\_on\_error** function enables you to control error handling for a specific segment of a Vuser script. To mark the segment, enclose it with **lr\_continue\_on\_error(1);** and **lr\_continue\_on\_error(0);** statements. The new error settings apply to the enclosed Vuser script segment. See the paragraphs below for details.

For example, if you enable the Continue on Error run-time setting and a Vuser encounters an error during replay of the following script segment, the Vuser continues executing the script:

```
web_link("EBOOKS",
    "Text=EBOOKS",
    "Snapshot=t2.inf",
    LAST);
web_link("Find Rocket eBooks",
    "Text=Find Rocket eBooks",
    "Snapshot=t3.inf",
    LAST);
```

To instruct the Vuser to continue on error for a specific segment of the script, enclose the segment with the appropriate **lr\_continue\_on\_error** statements:

```
lr_continue_on_error(1);
web_link("EBOOKS",
    "Text=EBOOKS",
    "Snapshot=t2.inf",
    LAST);
web_link("Find Rocket eBooks",
```

```
"Text=Find Rocket eBooks",
"Snapshot=t3.inf",
LAST);
lr_continue_on_error(0);
```

## Additional Debugging Information

### General Debugging Tip

VuGen can be used as a regular text editor. You can open any text file in it and edit it. When an error message is displayed during replay in the output window below, you can double click on it and VuGen jumps the cursor to the line of the test that caused the problem. You can also place the cursor on the error code and press F1 to view the online help explanation for the error code.

### Using C Functions for Tracing

You can use the C interpreter trace option (in version 230 or higher) to debug your Vuser scripts. The `ci_set_debug` statement allows trace and debug to be turned on and off at specific points in the script.

```
ci_set_debug(ci_this_context, int debug, int trace);
```

For example, you could add the following statements to your script:

```
ci_set_debug(ci_this_context, 1, 1) /* turn ON trace =; debug */
ci_set_debug(ci_this_context, 0, 0) /* turn OFF trace =; debug */
```

### Additional C Language Keywords

When you run a C script in VuGen, its parser uses the built-in C interpreter to parse the functions in the script. You can add keywords that are not part of the standard parser's library. By default, several common C++ keywords are added during installation, such as `size_t` and `DWORD`. You can edit the list and add additional keywords for your environment.

### Add Additional Keywords

1. Open the `vugen_extra_keywords.ini` file, located in your machine's <Windows> or <Windows>/System directory.
2. In the `EXTRA_KEYWORDS_C` section, add the desired keywords for the C interpreter.

The file has the following format:

```
[EXTRA_KEYWORDS_C]
FILE=
size_t=
WORD=
DWORD=
LPCSTR=
```

### Examining Replay Output

Look at the replay output (either from within VuGen, or the file `output.txt` representing the output of the VuGen driver). You may also change the run-time settings options in VuGen to select more

extensive logging in order to obtain a more detailed log output of the replayed test.

## Working with Breakpoints

VuGen lets you include breakpoints in your Vuser scripts to help you to debug the scripts. Breakpoints pause script execution at specified points in the script. This enables you to analyze the effects of the script on your application at pre-determined points during script execution. For task details, see ["How to Debug Scripts with Breakpoints" on page 394](#). A breakpoint symbol (●) in the left margin of the script indicates the presence of a breakpoint. In addition, VuGen highlights the line in the script.

You can disable a breakpoint if the breakpoint is temporarily not required. A white dot inside the Breakpoint symbol indicates a disabled breakpoint (○). When a breakpoint is disabled, script execution continues at the disabled breakpoint and is paused at the following enabled breakpoint. You use the Breakpoints pane to enable and disable breakpoints. In addition, the breakpoints pane enables you to delete an existing breakpoint or delete all existing breakpoints. To display the Breakpoints pane, click **View > Debug > Breakpoints**.

To run a script with breakpoints, begin running the script as usual. VuGen pauses script execution when it reaches a breakpoint. You can examine the effects of the script run up to the breakpoint, make any necessary changes, and then restart the script from the breakpoint.

To resume execution, select **Replay > Run**. Once restarted, the script continues until it encounters another breakpoint or the end of the script.

## Watching Expressions and Variables

VuGen's Watch pane enables you to monitor variables while a script runs. The list of variables that you want to watch is known as the watch list, and is displayed in the watch pane. To display the Watch pane, click **View > Debug > Watch**. You can add only variables to the watch list - you cannot add expressions to the watch list. You can add, edit, or remove variables within the watch list by using the Watch pane's toolbar buttons. You can sort the columns in the watch pane by expression, value, or type name by clicking the column headers. For details on other debugging features in VuGen, see ["Debugging - Overview" on page 388](#).

**Note:** You can monitor variables only when execution of a Vuser script is in the **Paused** state.

### Adding a New Watch to the Watch List

You can add a new watch expression only when execution of a Vuser script is in the **Paused** state.

To add a new watch:

1. Click **View > Debug > Watch** to open the Watch pane.
2. Click the **Add Watch** button . The Add New Watch dialog box opens.
3. In the **Expression** field, enter the variable that you want to watch, and then click **OK**. VuGen adds the variable to the list of expressions in the watch list.

Note: You can add only variables to the watch list - you cannot add expressions to the watch list.

## Editing a Watch Expression

Note: You can edit a watch expression only when execution of a Vuser script is in the **Paused** state.

To edit a watch expression:

1. Click **View > Debug > Watch** to open the Watch pane.
2. In the watch list, select the expression that you want to edit, and then click the **Edit Watch Expression** button . The Edit Watch dialog box opens.
3. In the **Expression** field, modify the existing variable as required, and then click **OK**. VuGen displays the modified variable in the list of variables in the watch list.

## Deleting a Watch Expression

Note: You can delete a watch expression only when execution of a Vuser script is in the **Paused** state.

To delete a watch expression:

1. Click **View > Debug > Watch** to open the Watch pane.
2. In the Watch pane, select the expression that you want to delete, and then click the **Delete Watch** button . VuGen deletes the selected expression from the list of expressions in the watch list.

## Deleting All Watch Expressions From the Watch List

Note: You can delete watch expressions only when execution of a Vuser script is in the **Paused** state.

To delete all watch expressions from the watch list:

1. Click **View > Debug > Watch** to open the Watch pane.
2. Click the **Delete All Watches** button . VuGen deletes all the expressions from the watch list.

# Debugging Web Vuser Scripts

VuGen provides an additional tool to help you debug Web Vuser scripts—the Results Summary report.

You can specify whether or not a Web Vuser generates a Results Summary report during script execution. The Results Summary report summarizes the success or failure of each step in the Web Vuser scripts and allows you to view the Web page returned by each step. For additional details on working with the Results Summary report, select **Replay > Test Results** and click F1 to open the online help.

For more user interface information, see ["Scripting Options" on page 103](#).

**Note:** Transaction times may be increased when a Vuser generates a Results Summary report. Vusers can generate Results Summary reports only when run from VuGen. When you run a script from the Controller or Business Process Monitor, Vusers do not generate reports.

## How to Debug Scripts with Breakpoints

The following steps describe how to work with breakpoints. For concept details, see ["Working with Breakpoints" on page 392](#).

### Add a Breakpoint

To add a breakpoint:

Locate the cursor in the script where you want to insert the breakpoint and then do one of the following:

- Select **Replay > Toggle Breakpoint**.
- Press **F9**.
- Click in the left margin if the script, adjacent to where you want to insert the breakpoint.

The **Breakpoint** symbol (●) appears in the left margin of the script, and VuGen highlights the line in the script.

### Delete a Breakpoint

To delete a breakpoint:

Locate the cursor in the script where you want to delete the breakpoint and then do one of the following:

- Select **Replay > Toggle Breakpoint**.
- Press **F9**.
- Click the breakpoint symbol left margin if the script.

The **Breakpoint** symbol (●) is removed from the left margin of the script.

### Enable/Disable a Breakpoint

To disable a breakpoint:

Click **View > Debug > Breakpoints** to display the Breakpoints pane.

- Select the appropriate **Enable** check box to enable a breakpoint. The **Breakpoint** symbol (●) appears in the left margin of the script.
- Clear the appropriate **Enable** check box to disable a breakpoint. The **Disabled Breakpoint** symbol (○) appears in the left margin of the script.

When a breakpoint is disabled, script execution continues at the disabled breakpoint and is paused at the following enabled breakpoint.

## Manage Breakpoints

The Breakpoints pane allows you to remove, enable, and disable breakpoints in a Vuser script. For user interface details, see ["Breakpoints Pane" on page 135](#).

### Navigate to a specific breakpoint in a Vuser script

To navigate to a specific breakpoint in a Vuser script, perform one of the following:

- In the Breakpoints pane, select the specific breakpoint to which you want to navigate, and then click the **Go to source** button .
- In the Breakpoints pane, double-click the breakpoint to which you want to navigate.

The cursor flashes in the Editor at the start of the line containing the breakpoint.

### Run a Script With Breakpoints

Begin running the script as usual. VuGen pauses script execution when it reaches a breakpoint. You can examine the effects of the script run up to the breakpoint, make any necessary changes, and then restart the script from the breakpoint.

To resume execution, select **Replay > Run**. Once restarted, the script continues until it encounters another breakpoint or the end of the script.

## Enhancing a Script for Load Testing

The **Enhancing a Script for Load Testing** section explains the features that VuGen provides to enable you to create Vuser scripts that will be able to accurately generate load. This includes features such as parameterization, transactions, and rendezvous points.

## Enhancing a Script for Load Testing - Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the sixth step, viewing the results of the replay of a Vuser script.



This task describes the additional things you can do to a Vuser script to prepare the script for load testing. All of the items in this task are optional.

### Add Parameterization

When you record a business process, VuGen generates a script that contains the actual values used during recording. Suppose you want to perform the script's actions (query, submit, and so forth) using different values from those recorded. To do this, you replace the recorded values with parameters. This is known as *parameterizing* the script. For more information, see ["Parameterizing - Overview" on page 408](#).

## Insert Transactions

You can insert transactions into your Vuser script either while recording the script or after recording the script. For task details, see "[How to Insert Transactions](#)" on page 398.

## Insert Rendezvous Points

You can synchronize Vusers to perform a task at exactly the same moment by creating a rendezvous point. When a Vuser arrives at the rendezvous point, it waits until all Vusers participating in the rendezvous arrive. When the designated number of Vusers arrive, the Vusers are released.

You can insert rendezvous points in one of the following ways:

- To insert a rendezvous point while recording, click the **Rendezvous** button  on the Recording toolbar and enter a name in the dialog box (not case sensitive).
- To insert a rendezvous point after recording, select **Design > Insert in Script > Rendezvous** and enter a name for the rendezvous point (not case sensitive).

When a rendezvous point is inserted, VuGen inserts a **lr\_rendezvous** function into the Vuser script. For example, the following function defines a rendezvous point named rendezvous1:

```
lr_rendezvous("rendezvous1");
```

For concept details, see "[Rendezvous Points](#)" on page 400.

## Insert VuGen Functions

You can insert VuGen functions at this point. For a list of some useful functions see "[Adding VuGen Functions - Overview](#)" on page 400.

## Insert Steps

You can insert a variety of steps into your script such as think time steps, debug messages, and output messages. For task details, see "[How to Insert Steps into a Script](#)" on page 406.

## Insert Comments

VuGen allows you to insert comments between Vuser activities. You can insert a comment to describe an activity or to provide information about a specific operation. For example, if you are recording database actions, you could insert a comment to mark the first query, such as "This is the first query."

You can insert a comment in one of the following ways:

- To insert a comment while recording, click the **Insert Comment** button  on the Recording toolbar and enter the desired comment in the Insert Comment dialog box.
- To insert a comment after recording, select **Design > Insert in Script > Comment** and enter the comment.

The following script segment shows how a comment appears in a Vuser script:

```
/* <comments> */
```

## Insert Log Messages

You can use VuGen to generate and insert **Ir\_log\_message** functions into a Vuser script. For example, if you are recording database actions, you could insert a message to indicate the first query, "This is the first query."

To insert a log message, select **Design > Insert in Script > Log Message** and enter the message.

## Insert Synchronization Points (RTE Vusers only)

You can add synchronization functions to synchronize the execution of the Vuser script with the output from your application. Synchronization applies to RTE Vuser scripts only.

The following is a list of the available synchronization functions:

Function	Description
<b>TE_wait_cursor</b>	Waits for the cursor to appear at a specified location in the terminal window.
<b>TE_wait_silent</b>	Waits for the client application to be silent for a specified number of seconds.
<b>TE_wait_sync</b>	Waits for the system to return from X-SYSTEM or Input Inhibited mode.
<b>TE_wait_text</b>	Waits for a string to appear in a designated location.
<b>TE_wait_sync_transaction</b>	Records the time that the system remained in the most recent X-SYSTEM mode.

For details about synchronization in RTE Vuser scripts, see "[RTE Synchronization Overview](#)" on [page 766](#).

## Transaction Overview

You define *transactions* to measure the performance of the server. Each transaction measures the time it takes for the server to respond to specified Vuser requests. These requests can be simple tasks such as waiting for a response for a single query, or complex tasks, such as submitting several queries and generating a report.

To measure a transaction, you insert Vuser functions to mark the beginning and the end of a task. Within a script, you can mark an unlimited number of transactions, each transaction with a different name.

For LoadRunner, the Controller measures the time that it takes to perform each transaction. After the test run, you analyze the server's performance per transaction using the Analysis' graphs and reports.

Before creating a script, you should determine which business processes you want to measure. You then mark each business process or sub-process as a transaction.

Transaction names cannot contain a "\_" or "@" symbol. This will cause errors to occur when attempting to open the Analysis Cross Results graphs.

You can create transactions either during or after recording. For task details, see "[How to Insert Transactions](#)" below.

## How to Insert Transactions

You can insert a transaction into a Vuser script either while recording the script or after recording the script. The following steps describe different methods to insert transactions. For background information, see "[Transaction Overview](#)" on the previous page.

### Insert a transaction after recording

You use VuGen's Editor to insert a transaction after recording a Vuser script.

1. To mark the start of a transaction, locate the cursor in the script where you want to start the transaction, and then perform one of the following:
  - Select **Design > Insert in Script > Start Transaction**.
  - Press **Ctrl+T**.
  - Right-click in the script where you want to start the transaction and select **Insert > Start Transaction**.

VuGen inserts an **lr\_start\_transaction** statement into the Vuser script. Enter a transaction name into the new step.

2. To mark the end of a transaction, locate the cursor in the script where you want to end the transaction, and then perform one of the following:
  - Select **Design > Insert in Script > End Transaction**.
  - Press **Ctrl+Shift+T**.
  - Right-click in the script where you want to end the transaction and select **Insert > End Transaction**.

VuGen inserts an **lr\_end\_transaction** statement into the Vuser script. Enter a transaction name into the new step.

3. To simultaneously mark the start and end of a transaction:
  - a. Select the steps that you want to include in the transaction.
  - b. Select **Design > Insert in Script > Surround with Transaction**, or right-click inside the selection and select **Surround with Transaction**, or press **Shift+Ctrl+I**.

The Surround with Transaction dialog box opens.

- c. Enter a name for the transaction, and then click **OK**.

VuGen inserts an **Ir\_start\_transaction** statement before the first selected step, and an **Ir\_end\_transaction** statement after the last selected step.

## Insert a transaction while recording

- To mark the start of a transaction, click the **Start Transaction** button  on the Recording toolbar, enter a transaction name, and click **OK**. When the script is generated, VuGen inserts an **Ir\_start\_transaction** statement into the Vuser script.
- To mark the end of a transaction, click the **End Transaction** button  on the Recording toolbar and select the transaction to close. When the script is generated, VuGen inserts an **Ir\_end\_transaction** statement into the Vuser script.

### Notes:

- You can create *nested* transactions—transactions within transactions. If you nest transactions, close the inner transactions before closing the outer ones—otherwise the transactions won't be analyzed properly. However, transactions must be contained within a single **action** section.
- Transaction names must be unique and may contain letters or numbers. Do not use the following characters: . , : # / \ <.
- A failed transaction does not automatically set the script's Replay status to Failed.

## How to Display Transactions

The following steps describe how to display different types of transactions when viewing them in the task pane. For background information, see "[Transaction Overview](#)" on page 397.

### Display Hidden Transactions

To display the hidden transactions—the non-primary and client side transactions—click the button adjacent to **Show hidden transactions** at the bottom of the transaction list. VuGen lists the hidden transactions in gray. To hide them, click the button again.

### Display Transactions With Errors

Transactions with errors are those that do not measure any server steps, or those with illegal names. To show the transactions with errors, click the **Show transactions with errors** button. VuGen lists the transactions with errors in red. To hide them, click the button again.

### Display Transactions for Non-primary Steps

To show the transactions for non-primary steps, you need to display all of the thumbnails. Select

**View > Show All Thumbnails.**

## Rendezvous Points

When performing load testing, you need to emulate heavy user load on your system. To accomplish this, you synchronize Vusers to perform a task at exactly the same moment. You configure multiple Vusers to act simultaneously by creating a rendezvous point. When a Vuser arrives at the rendezvous point, it waits until all Vusers participating in the rendezvous arrive. When the designated number of Vusers arrive, the Vusers are released.

You designate the meeting place by inserting a rendezvous point into your Vuser script. When a Vuser executes a script and encounters the rendezvous point, script execution is paused and the Vuser waits for permission from the Controller to continue. After the Vuser is released from the rendezvous, it performs the next task in the script.

For task details, see "[Enhancing a Script for Load Testing - Overview](#)" on page 395.

**Note:** Rendezvous points are effective only in Action sections—not init or end sections.

## Adding VuGen Functions - Overview

This section contains useful VuGen functions that you may want to add to your script while debugging or preparing your script for load testing.

### Obtaining Vuser Information

You can add the following functions to your Vuser scripts to retrieve Vuser information:

Function	Description
<code>lr_get_attrib_string</code>	Returns a command line parameter string.
<code>lr_get_host_name</code>	Returns the name of the machine running the Vuser script.
<code>lr_get_master_host_name</code>	Returns the name of the machine running the Controller. Not applicable when working with the HP Business Service Management.
<code>lr_whoami</code>	Returns the name of a Vuser executing the script. Not applicable when working with the HP Business Service Management.

In the following example, the `lr_get_host_name` function retrieves the name of the computer on which the Vuser is running.

```
my_host = lr_get_host_name( );
```

For more information about the above functions, see the Function Reference ([Help > Function Reference](#)).

## Sending Messages to Output

Using the Message type functions in your Vuser script, you can send customized error and notification messages to the output and log files, and to the Test Report summary. For example, you could insert a message that displays the current state of the client application. The LoadRunner Controller displays these messages in the Output window. You can also save these messages to a file.

When working with HP Business Service Management, you can use Message type functions to send error and notification messages to the Web site or Business Process Monitor log files. For example, you could insert a message that displays the current state of the Web-based application.

**Note:** Do not send messages from within a transaction as this may lengthen the transaction execution time and skew the transaction results.

You can use the following message functions in your Vuser scripts:

Function	Description
<b>lr_debug_message</b>	Sends a debug message to the Output window or the Business Process Monitor log file.
<b>lr_error_message</b>	Sends an error message to the Output window, Test Results report, or the Business Process Monitor log files.
<b>lr_get_debug_message</b>	Retrieves the current message class.
<b>lr_log_message</b>	Sends an output message directly to the log file, <i>output.txt</i> , located in the Vuser script folder. This function is useful in preventing output messages from interfering with TCP/IP traffic.
<b>lr_output_message</b>	Sends a message to the Output window, Test Results report, or the Business Process Monitor log files.
<b>lr_set_debug_message</b>	Sets a message class for output messages.
<b>lr_vuser_status_message</b>	Sends a message to the Vuser status area in the Controller. Not applicable when working with the HP Business Service Management.
<b>lr_message</b>	Sends a message to the Vuser log and Output window or the Business Process Monitor log files.

The behavior of the **lr\_message**, **lr\_output\_message**, and **lr\_log\_message** functions are not affected by the script's debugging level in the Log run-time settings—they will always send messages.

Using the **Ir\_output\_message**, and **Ir\_error\_message** functions, you can also send meaningful messages to the Test Results summary report. For information, see ["Viewing Replay Results" on page 479](#)

## General Vuser Functions

The general Vuser functions are also called LR functions because each LR function has an **Ir** prefix. The LR functions can be used in any type of Vuser script. The LR functions enable you to:

- Get run-time information about a Vuser, its Vuser Group, and its host.
- Add transactions and synchronization points to a Vuser script. For example, the **Ir\_start\_transaction** (**Ir.start\_transaction** in Java) function marks the beginning of a transaction, and the **Ir\_end\_transaction** (**Ir.end\_transaction** in Java) function marks the end of a transaction. See ["Enhancing a Script for Load Testing" on page 395](#) for more information.
- Send messages to the output, indicating an error or a warning.

For details see the *Function Reference* (**Help > Function Reference**).

## Protocol-Specific Vuser Functions

In addition to the general Vuser functions, VuGen also generates and inserts protocol-specific functions into the Vuser script while you record.

The protocol-specific functions are particular to the type of Vuser that you are recording. For example, VuGen inserts LRS functions into a Windows Sockets script.

By default, VuGen's automatic script generator creates Vuser scripts in C for most protocols, and in Java for Java type protocols. You can instruct VuGen to generate code in Visual Basic or Javascript. For more information, see ["General > Script Node" on page 203](#).

All standard conventions apply to the scripts, including control flow and syntax. You can add comments and conditional statements to the script just as you do in other programming languages.

The following segment from a Web Vuser script shows several functions that VuGen recorded and generated in a script:

```
#include "as_web.h"
Action1()
{
    web_add_cookie("nav=140; DOMAIN=dogbert");
    web_url("dogbert",
        "URL=http://dogbert/",
        "RecContentType=text/html",
        LAST);
    web_image("Library",
        "Alt=Library",
        LAST);
    web_link("1 Book Search:",
        "Text=1 Book Search:",
```

```
LAST);  
lr_start_transaction("Purchase_Order");  
...
```

For more information about using C functions in your Vuser scripts, see the Function Reference (Help > Function Reference). For more information about modifying a Java script, see "[Java Vuser Protocol - Manually Programming Scripts](#)" on page 667.

**Note:** The C Interpreter used for running Vuser scripts written in C, only supports the ANSI C language. It does not support the Microsoft extensions to ANSI C.

## Encrypting Text

You can encrypt text within your script to protect your passwords and other confidential text strings. You can perform encryption both automatically, from the user interface, and manually, through programming. You can restore the string at any time, to determine its original value. When you encrypt a string, it appears in the script as a coded string. VuGen uses 32-bit encryption.

In order for the script to use the encrypted string, it must be decrypted with **lr\_decrypt**.

```
lr_start_transaction(lr_decrypt("3c29f4486a595750"));
```

For task details, see "[How to Encrypt/Decrypt Text](#)" on the next page.

## Password Encoding

You can encode passwords in order to use the resulting strings as arguments in your script or parameter values. For example, your Web site may include a form in which the user must supply a password. You may want to test how your site responds to different passwords, but you also want to protect the integrity of the passwords. The **Password Encoder** enables you to encode your passwords and place secure values into the table.

To encode a password, select **Start > All Programs > HP Software > HP LoadRunner > Tools > Password Encoder**.

For task details, see "[How to Encode a Password](#)" on the next page.

For user interface details, see "[Password Encoder Dialog Box](#)" on the next page.

## Encrypting Text

You can encrypt text within your script to protect your passwords and other confidential text strings. You can perform encryption both automatically, from the user interface, and manually, through programming. You can restore the string at any time, to determine its original value. When you encrypt a string, it appears in the script as a coded string. VuGen uses 32-bit encryption.

In order for the script to use the encrypted string, it must be decrypted with **lr\_decrypt**.

```
lr_start_transaction(lr_decrypt("3c29f4486a595750"));
```

For task details, see "[How to Encrypt/Decrypt Text](#)" on the next page.

## How to Encrypt/Decrypt Text

This task describes how to encrypt and decrypt strings in your code. For background information, see "[Encrypting Text](#)" on the previous page.

### Encrypt a string

1. Select the text you want to encrypt.
2. Select **Encrypt string (string)** from the right-click menu.

### Restore an encrypted string

1. Select the string you want to restore.
2. Select **Restoreencrypted string (string)** from the right-click menu.

For more information on the **Ir\_decrypt** function, see the Function Reference (**Help > Function Reference**).

## How to Encode a Password


This task describes how to encode a password. You can encode passwords in order to use the resulting strings as arguments in your script or parameter values. For example, your Web site may include a form in which the user must supply a password. You may want to test how your site responds to different passwords, but you also want to protect the integrity of the passwords.

### Encode a password

1. From the Windows menu, select **Start > All Programs > HP Software > HP LoadRunner > Tools > Password Encoder**. The Password Encoder dialog box opens.
2. Enter the password in the **Password** box.
3. Click **Generate**. The Password Encoder encrypts the password and displays it in the **Encoded String** box.
4. Use the **Copy** button to copy and paste the encoded value into the Data Table.

## Password Encoder Dialog Box

This dialog box enables you to generate encoded passwords.



To access	<b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Tools &gt; Password Encoder</b>
Relevant tasks	<a href="#">"How to Encode a Password" on the previous page</a>
See also	<a href="#">"Password Encoding" on page 403</a>

User interface elements are described below:

UI Element	Description
<b>Copy</b>	Copy the results from the encoded string field to paste them to the Data table containing your list of parameters.
<b>Encoded String</b>	The encoded results are displayed here.
<b>Generate</b>	Click this to generate the encoded password.
<b>Password</b>	Enter the password you want to encode here.

## How to Create a Controller Scenario from VuGen

**Note:** The following section only applies to LoadRunner. For information on integrating scripts into Business Process profiles, see the HP Business Service Management documentation.

Normally, you create a scenario from the LoadRunner Controller. You can also create a basic scenario from VuGen using the current script.

To create this type of scenario, select **Tools > Create Controller Scenario** and complete the dialog box. For user interface details, see "[Create Controller Scenario Dialog Box" on the next page.](#)

For more information, see the HP Controller User Guide.

# How to Insert Steps into a Script

The following steps describe how to add different types of steps into a Vuser script.

## Insert Think Time Steps

The time that a user waits between performing successive actions is known as the *think time*. Vusers use the `Ir_think_time` function to emulate real-user think time. When you record a Vuser script, VuGen records the actual think times and inserts appropriate `Ir_think_time` statements into the Vuser script. You can edit the recorded `Ir_think_time` statements, and manually add more `Ir_think_time` statements to a Vuser script.

To add a think time step, select **Design > Insert in Script > New Step > Think Time** and specify the desired think time - in seconds.

**Note:** When you record a Java Vuser script, `Ir_think_time` statements are not generated in the Vuser script.

You can use the run-time settings to influence how the `Ir_think_time` statements operate when you execute a Vuser script. For user interface details, see "[General > Think Time Node](#)" on page 350.

## Insert Debug Messages

You can add a debug or error message using VuGen's user interface. For debug messages you can indicate the level of the text message—the message is only issued when your specified level matches the message class. You set the message class using `Ir_set_debug_message`.

To insert a debug message, select **Design> Insert in Script >New Step > Debug Message** and complete the dialog box. For user interface details, see [Debug Message Dialog Box](#).

## Insert Error and Output Messages


For protocols that support the **Step Navigator**, such as Web, Winsock, and Oracle NCA, you can add an error or output message using the user interface. A common usage of this function is to insert a conditional statement, and issue a message if the error condition is detected.

To insert an error or output message, select **Design > Insert in Script >New Step > Error Message or Output Message**, and enter the message. An `Ir_error_message` or `Ir_output_message` function is inserted at the current point in the script.

**Note:** An Error Message step in a script does not automatically set the Replay status to Failed.

# Create Controller Scenario Dialog Box

This dialog box enables you to create a basic Controller scenario from within VuGen.



<b>To access</b>	<b>VuGen &gt; Tools &gt; Create Controller Scenario</b>
<b>Relevant tasks</b>	<a href="#">"How to Create a Controller Scenario from VuGen" on page 405</a>

User interface elements are described below:

UI Element	Description
<b>Add script to current scenario</b>	If a scenario is currently open in the Controller and you want to add the script to this scenario, select this check box. If you clear the check box, LoadRunner opens a new scenario with the specified number of Vusers.
<b>Group Name</b>	For a manual scenario, users with common traits are organized into groups. Specify a new group name for the Vusers.
<b>Load Generator</b>	The name of the machine that will run the scenario.
<b>Results Directory</b>	Enter the desired location for the results.
<b>Script Name</b>	For a goal-oriented scenario, specify a script name.

, continued

<b>Select Scenario Type</b>	<ul style="list-style-type: none"><li>• <b>Goal Oriented Scenario.</b> LoadRunner automatically builds a scenario based on the goals you specify.</li><li>• <b>Manual Scenario.</b> The scenario is created manually by specifying the number of Vusers to run.</li></ul>
-----------------------------	---

## Parameters

The **Parameters** section describes who how to insert, define and modify parameters.

### Parameterizing - Overview

When you record a business process, VuGen generates a script that contains the actual values used during recording. Suppose you want to perform the script's actions (query, submit, and so forth) using different values from those recorded. To do this, you replace the recorded values with parameters. This is known as *parameterizing* the script.

The resulting Vusers substitute the parameter with values from a data source that you specify. The data source can be either a file, or internally generated variables. For details, see "["Parameter Types" on page 410](#).

Parameters appear inside a Vuser script within parameter delimiters. By default, VuGen uses "{" and "}" as the left and right parameter delimiters, but you can modify these delimiters if required. In addition, you can modify the background color and outline color of parameters in a script. For details, see "["Scripting Options" on page 103](#).

#### Delimiter Example

Script section as recorded.

"value=UNIX"

Script section after "UNIX" has been replaced with the "Operating System" parameter.

"value={Operating System}"

You can use parameterization only for the arguments within a function. You cannot parameterize text strings that are not function arguments. In addition, not all function arguments can be parameterized. For details on which arguments you can parameterize, see the Function Reference ([Help > Function Reference](#)) for each function.

Input parameters are parameters whose values you define in the design stage before running the script. Output parameters you define during design stage, but they acquire values during test execution. Output parameters are often used with Web Service calls. Use care when selecting a parameter for your script during design stage, make sure that it is not an empty Output parameter.

#### Example

Let's say you recorded a Vuser script while operating a Web application. VuGen generated the

following statement that searches a library's database for the title "UNIX":

```
web_submit_form("db2net.exe",
    ITEMDATA,
    "name=library.TITLE",
    "value=UNIX",
    ENDITEM,
    "name=library.AUTHOR",
    "value=",
    ENDITEM,
    "name=library.SUBJECT",
    "value=",
    ENDITEM,
    LAST);
```

When you replay the script using multiple Vusers and iterations, you do not want to repeatedly use the same value, UNIX. Instead, you replace the constant value with a parameter:

```
web_submit_form("db2net.exe",
    ITEMDATA,
    "name=library.TITLE",
    "value={Book_Title}",
    ENDITEM,
    "name=library.AUTHOR",
    "value=",
    ENDITEM,
    "name=library.SUBJECT",
    "value=",
    ENDITEM,
    LAST);
```

For task details, see ["How to Create a Parameter" on page 412](#).

To enable some recorded Vuser scripts to replay correctly, it may be necessary to implement correlation. Correlation is used when a recorded script includes a dynamic value (such as a session ID) and therefore cannot be successfully replayed. To resolve this, you convert the dynamic value into a variable—thereby enabling your script to replay successfully. For details, see ["Correlation Overview" on page 274](#).

## VTS and Parameterization

### What is VTS?

HP LoadRunner Virtual Table Server [VTS] is a web-based application that works with LoadRunner Vuser scripts. VTS offers an alternative to standard LoadRunner parameterization.

When you use standard LoadRunner parameterization, each Vuser is assigned parameter values from a dedicated set of values - parameter values are not shared between Vusers. In contrast, VTS enables you to assign parameter values from a single set of parameter values to multiple Vusers. This may enable you to more accurately emulate a real-user environment.

VTS is composed of two components, VTS-Client and VTS-Server. VTS-Client is a set of API functions that are used to access data in VTS-Server. Because the VTS API functions are integrated into LoadRunner, there is no need to install VTS-Client. VTS-Server includes a table that contains parameter values that can be used by your Vuser scripts. The VTS table is composed of columns and rows. Each column represents a set of values that can be assigned to a specific parameter in your Vuser scripts. The cells within a column contain the actual values that are assigned to the parameter.

**Note:** Significant changes were made to VTS in LoadRunner version 11.52. When upgrading to VTS 11.52 or later, these changes may result in various compatibility issues. For details on script modifications that are required in order to resolve these compatibility issues, see the VTS documentation that is available from the **VTS > Help** menu.

- For details on how to install VTS-Server, see the *HP LoadRunner Installation Guide*. After installing VTS-Server, you can access further information about VTS from the **VTS > Help** menu.
- For details on how to use VTS functionality in TruClient Vuser scripts, see "[How to Use VTS in TruClient](#)" on page 539.

## Parameter Types

Every parameter is defined by the type of data it contains. This section contains information on the different parameter types.

### File Parameter Types

Data files hold data that a Vuser accesses during script execution. Data files can be local or global. You can specify an existing ASCII file, use VuGen to create a new one, or import a database file. Data files are useful if you have many known values for your parameter.

The data in a data file is stored in the form of a table. One file can contain values for many parameters. Each column holds the data for one parameter. Column breaks are marked by a delimiter, for example, a comma.

In the following example, the data file contains ID numbers and first names:

```
id,first_name
120,John
121,Bill
122,Tom
```

**Note:** When working with languages other than English, save the parameter file as a UTF-8 file. In the Parameter Properties window, click **Edit with Notepad**. In Notepad, save the file as a text file with UTF-8 type encoding.

## Table Parameter Types

The Table parameter type is meant for applications that you want to test by filling in table cell values. Whereas the file type uses one cell value for each parameter occurrence, the table type uses several rows and columns as parameter values, similar to an array of values. Using the table type, you can fill in an entire table with a single command. This is common in SAP GUI Vusers where the **sapgui\_table\_fill\_data** function fills the table cells.

## XML Parameter Types

Used as a placeholder for multiple valued data contained in an XML structure. You can use an XML type parameter to replace the entire structure with a single parameter. For example, an XML parameter called **Address** can replace a contact name, an address, city, and postal code. Using XML parameters for this type of data allows for cleaner input of the data, and enables cleaner parameterization of Vuser scripts. We recommend that you use XML parameters with Web Service scripts or for SOA services.

## Internal Data Parameter Types

Internal data is generated automatically while a Vuser runs, such as Date/Time, Group Name, Iteration Number, Load Generator Name, Random Number, Unique Number, and Vuser ID.

- Custom: You can specify the parameter data type.
- Date/Time: The current date/time. You can specify the format and the offset in the Parameter Properties dialog box.
- Group Name: The name of the Vuser Group. If there is no Vuser Group (for example, when running a script from VuGen) the value is always **none**.
- Iteration Number: The current iteration number.
- Load Generator Name: The name of the Vuser script's load generator (the computer on which the Vuser is running).
- Random Number: A random number within a range of values that you specify.
- Unique Number: Assigns a range of numbers to be used for each Vuser. You specify the start value and the block size (the amount of unique numbers to set aside for each Vuser). For example, if you specify a start value of 1 and a block size of 100 the first Vuser can use the numbers 1 to 100, the second Vuser can use the numbers 201-300, and so on.
- Vuser ID: The ID number assigned to the Vuser by the Controller during a scenario run. When you run a script from VuGen, the Vuser ID is always -1.

**Note:** This is not the ID number that appears in the Vuser window—it is a unique ID number generated at runtime.

## User-Defined Function Parameters

Data that is generated using a function from an external DLL. A user-defined function replaces the parameter with a value returned from a function located in an external DLL.

Before you assign a user-defined function as a parameter, you create the external library (DLL) with the function. The function should have the following format:

```
__declspec(dllexport) char *<functionName>(char *, char *)
```

The arguments sent to this function are both NULL.

When you create the library, we recommend that you use the default dynamic library path. That way, you do not have to enter a full path name for the library, but rather, just the library name. VuGen's bin folder is the default dynamic library path. You can add your library to this folder.

The following are examples of user-defined functions:

```
__declspec(dllexport) char *UF_GetVersion(char *x1, char *x2) {return "Ver2.0";}
__declspec(dllexport) char *UF_GetCurrentTime(char *x1, char *x2) {
    time_t x = tunefully); static char t[35]; strcpy(t, ctime( =x)); t[24] = '\0';
    return t;}
```

## How to Create a Parameter

This task describes how to create a parameter.

### 1. Select the value you want to parameterize

You can do this step from both the **Editor** and from the **Steps Navigator** pane.

Select the value you want to parameterize, right-click and select **Replace with Parameter**.

#### Notes:

- When creating XML parameters in script view, you must select only the inner xml, without the bounding tags. For example, to parameterize the complex data structure `<A><B>Belement</B><C>Celement</C></A>`, select the whole string, `<B>Belement</B><C>Celement</C>`, and replace it with a parameter.
- When parameterizing Java Record Replay or Java Vuser scripts, you must parameterize complete values, not parts of a value.

#### Steps Navigator pane

Right-click on a step and select **Show Arguments**. Click the **ABC** icon next to the argument that you want to parameterize.

### 2. Create a new parameter in the Select or Create Parameter dialog box

Specify the parameters name and type in the **Select or Create Parameter** dialog box. For user interface details, see "[Select or Create Parameter Dialog Box](#)" on page 425.

### 3. Add a list of required values

From the **Select or Create Parameter** dialog box, select **Properties**. Create a table and add entries to serve as the list of values for your parameter. For user interface details, see

["Parameter Properties Dialog Box" on page 426.](#)

#### 4. Modify the parameter braces - optional

You can modify the braces that surround parameters in the **Configure Parameter Braces** dialog box. You can access the dialog box from the following locations:

- Right-click on the **Parameters** node in the **Solution Explorer** pane and select **Configure Parameter Delimiters**.
- **Design > Parameters > Configure Parameter Delimiters**
- **Tools > Options > Parameters**

For user interface details, see [Parameter Delimiters Configuration Dialog Box](#).

## Data Assignment Methods for File/Table/XML Parameters

When using values from a file, VuGen lets you specify the way in which you assign data from the source to the parameters. The following methods for assigning data are available:

### Sequential

Assigns data to a Vuser sequentially. As a running Vuser accesses the data table, it takes the next available row of data.

If there are not enough values in the data table, VuGen returns to the first value in the table, continuing in a loop until the end of the test.

### Random

Assigns a random value from the data table every time a new parameter value is requested.

When running a scenario in LoadRunner, or a script in HP Business Process Monitor, you can specify a seed number for random sequencing. Each seed value represents one sequence of random values used for test execution. Whenever you use this seed value, the same sequence of values is assigned to the Vusers in the scenario. You enable this option if you discover a problem in the test execution and want to repeat the test using the same sequence of random values.

### Unique

Assigns a unique sequential value to the parameter for each Vuser. Ensure that there is enough data in the table for all Vusers and their iterations. If you have 20 Vusers and you want to perform 5 iterations, your table must contain at least 100 unique values.

If you run out of unique values, VuGen behaves according to the option you select in the **When out of values** field. For more information, see ["Parameter Properties Dialog Box" on page 426.](#)

**Note:** For LoadRunner users: If a script uses Unique file parameterization, running more than one Vuser group with that script in the same scenario may cause unexpected scenario results.

For more information about Vuser groups in scenarios, see the Function Reference.

- For details on the different data assignment and update methods, see "[Data Assignment and Update Methods for File/Table/ XML Parameters](#)" below.
- For details on how parameters behave when the number of iterations do not match the number of values in the parameter file, see "["Vuser Behavior in the Controller \(LoadRunner Only\)" on the next page](#).

## **Data Assignment and Update Methods for File/Table/ XML Parameters**

For File, Table, and XML type parameters, the Data Assignment method that you select, together with your choice of Update method, affect the values that the Vusers use to substitute parameters during the scenario run.

The Data Assignment method is determined by the **Select next row** field, and the Update method is determined by the **Update value on** field.

The following table summarizes the values that Vusers use depending on which Data Assignment and Update properties you selected:

Update Method	Data Assignment Method		
	Sequential	Random	Unique
<b>Each iteration</b>	The Vuser takes the <i>next</i> value from the data table for each iteration.	The Vuser takes a <i>new random</i> value from the data table for each iteration.	The Vuser takes a value from the next unique position in the data table for each iteration.
<b>Each occurrence</b> (Data Files only)	The Vuser takes the <i>next</i> value from the data table for each occurrence of the parameter, even if it is within the same iteration.	The Vuser takes a <i>new random</i> value from the data table for each occurrence of the parameter, even if it is within the same iteration.	The Vuser takes a <i>new unique</i> value from the data table for each occurrence of the parameter, even if it is within the same iteration.
<b>Once</b>	The value assigned in the first iteration is used for all subsequent iterations for each Vuser.	The random value assigned in the first iteration is used for all iterations of that Vuser.	The unique value assigned in the first iteration is used for all subsequent iterations of the Vuser.

### **Examples**

Assume that your table/file has the following values:

**Kim; David; Michael; Jane; Ron; Alice; Ken; Julie; Fred**

### Sequential Method

- If you specify update on **Each iteration**, all the Vusers use Kim in the first iteration, David in the second iteration, Michael in the third iteration, and so on.
- If you specify update on **Each occurrence**, all the Vusers use Kim in the first occurrence, David in the second occurrence, Michael in the third occurrence, and so on.
- If you specify update **Once**, all Vusers take Kim for all iterations.

**Note:** If you select the **Sequential** method and there are not enough values in the data table, VuGen returns to the first value in the table, continuing in a loop until the end of the test.

### Random Method

- If you specify update on **Each iteration**, the Vusers use random values from the table for each iteration.
- If you specify update on **Each occurrence**, the Vusers use random values for each occurrence of the parameter.
- If you specify update **Once**, all Vusers take the first randomly assigned value for all the iterations.

### Unique Method

- If you specify update on **Each iteration**, for a test run of 3 iterations, the first Vuser takes Kim in the first iteration, David in the second, and Michael in the third. The second Vuser takes Jane, Ron, and Alice. The third Vuser, Ken, Julie, and Fred.
- If you specify update on **Each occurrence**, then the Vuser uses a unique value from the list for each occurrence of the parameter.
- If you specify update **Once**, the first Vuser takes Kim for all iterations, the second Vuser takes David for all iterations, and so on.

## **Vuser Behavior in the Controller (LoadRunner Only)**

When you set up a scenario to run a parameterized script, you can instruct the Vusers how to act when there are not enough values. The following table summarizes the results of a scenario using the following parameter settings:

- Select next row = **Unique**
- Update Value on = **Each iteration**
- When out of values = **Continue with last value**

Situation	Duration	Resulting Action
<b>More iterations than values</b>	<b>Run until completion</b>	When the unique values are finished, each Vuser continues with the last value, but a warning message is sent to the log indicating that the values are no longer unique.
<b>More Vusers than values</b>	<b>Run indefinitely or Run for ...</b>	Vusers take all of the unique values until they are finished. Then the test issues an error message <b>Error: Insufficient records for param &lt;param_name&gt; in table to provide the Vuser with unique data</b> . To avoid this, change the <b>When out of values</b> option in the Parameter properties or the <b>Select next row</b> method in the Parameter properties.
<b>One of two parameters are out of values</b>	<b>Run indefinitely or Run for ...</b>	The parameter that ran out of values, continues in a cyclic manner until the values of the second parameter are no longer unique.

## How to Work with Existing Parameters

This task describes how to replace values with pre-defined parameters.

Replace a value with a parameter

You can replace a value with an pre-defined parameter. In the script-editor, right-click on the relevant value and select one of the following options:

- **Replace with Parameter** > select a <pre-defined> parameter. The list of parameters include parameters which have the same original value or parameters that have not yet been used.
- **Replace with Parameter** > select a parameter from the **Parameter List** dialog box.

Replace multiple occurrences of a value with a parameter

You can replace multiple occurrences of a value with a parameter. To do this, in the script editor replace at least one occurrence of the value with a parameter. Right-click the parameter and select **Replace more occurrences**. Use **Search and Replace** to replace all of the values in the script with the selected parameter.

### Restore the original value

You can undo a parameter and restore the original value by right-clicking the parameter in the script editor and selecting **Restore original value**.

## XML Parameters

When you create a Web Service call to emulate a specific operation, the arguments in the operation may include complex structures with many values. You can use an XML type parameter to replace the entire structure with a single parameter.

You can create several value sets for the XML elements and assign a different value set for each iteration.

The XML parameter type supports complex schema types such as arrays, Choice, and <Any> elements.

When working with Web Service Input Arguments, you may encounter arrays and their sub-elements. You can define a single XML parameter that will contain values for all of the array elements.

You can create new XML type parameters directly from the Insert menu, similar to all other parameter types. For Web Services type scripts, you create an XML parameter directly from the Web Services Call properties.


**Caution:** For protocols using XML, replay fails to create a request when a parameterized input argument contains the ampersand (&) character.

## How to Create an XML Parameter from a Web Service Call

This task describes how to create a new XML Parameter from a Web Service Call. This procedure is in addition to the standard procedure to create a parameter. XML Parameters can also be created by using the standard procedure.

### Create an XML Parameter from a Web Service Call

1. Select the root element of the complex data structure. The right pane displays the argument's details.



2. Select **XML** in the right pane, and click the ABC icon. The Select or Create Parameter dialog box opens.
3. In the **Parameter name** box, enter a name for the parameter.
4. In the **Parameter type** box, select **XML** if it is not already selected.
5. Click **Properties** to assign a value set now, or **OK** to close the dialog box and assign values later.

## How to Create XML Parameters - Standard Method

This task describes how to create an XML type parameter without viewing the properties of a Web Service call. This is the most common way of parameterizing values for most protocols and parameter types.

For Web Service Scripts, we recommend that you create parameters from within a Web Service Call, as described in "["XML Parameters" on page 416](#)".

Create a new XML parameter

1. Select **Insert > New Parameter** or select a constant value in the Script view and select **Replace with a Parameter** from the right-click menu. The Select or Create Parameter dialog box opens.
2. In the **Parameter name** box, enter a name for the parameter.

3. In the **Parameter type** box, select **XML** if it is not already selected.
4. Click **Properties** to assign a value set now, or **OK** to close the dialog box and assign values later.

## How to Define XML Value Sets

This task describes how to create value sets for XML parameters.

Value sets are arrays that contain a set of values. Using the **Add Column** and **Duplicate Column** buttons, you can create multiple value sets for your parameter and use them for different iterations.

Schema	Set 1	Set 2	Set 3
Addr			
name	John Doe	Tom Smith	Kim Jones
street	2 Maple Ln.	33 Acorn Dr.	45 Jasper Ave.
city	NIL Delray Beach	NIL	NIL
state	FL	AZ	MA
zip	NIL 33452	NIL	NIL 02134
zip4			
phonenumbers			
PhoneNumber [..]			
PhoneNumber[1]	NIL	NIL	NIL

When using value sets, the number of array elements per parameter does not have to be constant.

You can use optional elements that will appear in one value set, but not in another. This allows you to vary the values you send for each of the iterations—some iterations can include specific array elements, while other iterations exclude them.

To exclude an optional element, click the small triangle in the upper left corner of the cell and insure that it is not filled in.


In the following example, **Set 1** and **Set 2** use the optional elements: **name**, **street**, and **state**. **Set 3** does not use a street name.

Schema	Set 1	Set 2	Set 3
Addr			
name	John Doe	Tom Smith	Kim Jones
street	2 Maple Ln.	33 Acorn Dr.	45 Jasper Ave.
city	NIL Delray Beach	NIL	NIL
state	FL	AZ	MA
zip	NIL 33452	NIL	NIL 02134
zip4			
phonenumbers			
PhoneNumber [..]			
PhoneNumber[1]	NIL	NIL	NIL

Set parameter element values


**1. View the Parameter Properties.**

If the Parameter Properties dialog box is not open, select **Vuser > Parameter List** and select the desired parameter. The dialog box shows a read-only view of the parameter values.



**2. Open the Data Parameterization box.**

Click the **Edit Data** button to open the Data Parameterization dialog box.



**3. Define value sets for the XML parameter.**

In the **Set** columns, insert values corresponding to the schema.

If a row says **NIL**, it implies that the element is nillable. To include a value for the nillable element, enter the value as usual. To mark a value as **nil**, click the NIL icon to fill it in. This erases any value that you may have assigned to the element. In the following example, the **city** element is nillable, but it is only marked as nil in **Set 2** and **Set3**—not in **Set 1**.

Schema	Set 1	Set 2	Set 3
Addr			
name	John Doe	Tom Smith	Kim Jones
street	2 Maple Ln.	33 Acorn Dr.	45 Jasper Ave.
city	NIL	Delray Beach	NIL
state	FL	AZ	MA
zip	NIL	33452	NIL
zip4			
phonenumbers			
PhoneNumber [...]			
PhoneNumber[1]	NIL	NIL	NIL

#### 4. Create additional value sets.

To insert more value sets, click **Add Column** and insert another set of values in the new column. To copy an existing value set, select a row in the value set you want to copy and click **Duplicate Column**.

#### 5. Copy arrays.

To duplicate an array element and its children, select the parent node and choose **Duplicate Array Element** from the right-click menu.

Schema	Set 1	Set 2	Set 3
phone-numbers			
PhoneNumber [...]			
PhoneNumber[1]	[ ]	[ ]	[ ]
description	Home	Home	Home
phone-number	888-8888	111-1111	444-4444
PhoneNumber[2]	[ ]	[ ]	[ ]
description	Office	Office	Office
phone-number	666-6666	222-2222	999-9999
PhoneNumber[3]	[ ]	[ ]	[ ]
description	Mobile	Mobile	Mobile
phone-number	3-3333	123-4567	


#### 6. Handle the <any> elements.

For **any** type elements, right-click **<any>** in the **Schema** column and select one of the available options. These options may vary depending on the location of the cursor.

- **Add Array Element.** Adds a sub-element under the root element.

- **Insert child.** Adds a sub-element to the selected element.
- **Insert sibling.** Adds a sub-element on the same level as the selected element.
- **Load XML.** Loads the element values from an XML file.
- **Save XML.** Saves the array as an XML file.
- **Copy XML.** Copies the full XML of the selected element to the clipboard.

Click the **Rename** text to provide a meaningful name for each array element.



#### 7. Remove unwanted columns.

To remove a value set, select it and click **Delete Column**.

#### 8. Save the changes.

Click **Apply** to save the changes and update the view in the Parameter Properties dialog box.

## How to Set an Assignment Method

This task describes how to set an assignment method. The assignment method indicates which of the value sets to use and how to use them. For example, you can instruct Vusers to use a new value set for each iteration and use the value sets sequentially or at random. For more information, see "[Data Assignment and Update Methods for File/Table/ XML Parameters](#)" on page 414.

### Define an assignment method

1. Open the Parameter Properties and select a parameter.
2. Define a data assignment method.

In the **Select next value** list, select a data assignment method to instruct the Vuser how to select the file data during Vuser script execution. The options are: **Sequential**, **Random**, or **Unique**. For more information, see "[Data Assignment Methods for File/Table/XML Parameters](#)" on page 413.

3. Select an update option for the parameter.

In the **Update value on** list, select an update option. The choices are **Each Iteration**, **Each Occurrence**, and **Once**. For more information, see "[Data Assignment and Update Methods for File/Table/ XML Parameters](#)" on page [414](#).

4. If you chose **Unique** as the data assignment method the **When out of values** and **Allocate Vuser values in the Controller** options become enabled.
  - **When out of values.** Specify what to do when there is no more unique data: **Abort Vuser**, **Continue in a cyclic manner**, or **Continue with last value**.
  - **Allocate Vuser values in the Controller** (for LoadRunner users only). Indicate whether you want to manually allocate data blocks for the Vusers. You can allow the Controller to automatically allocate a block size or you can specify the desired number of values. Select **Automatically allocate block size** or **Allocate x values for each Vuser**. For the second option, specify the number of values to allocate.

To track this occurrence, enable the **Extended Log > Parameter Substitution** option in the Log Run-Time settings. When there is not enough data, VuGen writes a warning message to the Vuser log: **No more unique values for this parameter in table <table\_name>**.

5. In the Parameter Properties dialog box, click **Close**.

The list of input arguments is replaced by the parameter name, and ABC button is replace by a table icon  which you can click to edit the parameter properties or un-parameterize the parameter.

## How to Modify XML Parameter Properties

This task describes how to modify XML parameter properties.

To modify XML parameter properties:

1. In the Step Navigator, right-click the required step and select **Show Arguments**. The Web Service Call Properties dialog box opens.
2. From the list of arguments, under **Input Arguments**, select the XML parameter. The right pane displays the parameter details.
3. To modify the XML parameter properties, select the **XML** check box, click the table icon  button, and then select **Parameter Properties**. The Parameter Properties dialog box opens.
4. Modify the parameter properties as desired.

## How to Set AUT Environment Parameters

When working with scripts stored in HP Application Lifecycle Management (ALM), you can work with different Application Under Test (AUT) environments.

AUT Environments are environments that you define in ALM that represent different testing configurations. By parameterizing the environment data, you can make your test more flexible and portable. Instead of running several scripts that use the same logic, but with different AUT environment constants, you can maintain a single script that uses AUT environment parameters.

You define environment-specific parameters in ALM's AUT Environment configuration. During the test run, ALM inserts these values into your script. For more details on working with AUT environments, refer to the *HP Application Lifecycle Management User Guide*.

This task describes how to define an AUT environment type parameter in your Vuser script.

1. Create a parameter in VuGen. Make sure the name of the parameter matches the name of the corresponding AUT environment parameter.
2. Set the parameter type to "**Custom parameter**".
3. Enter the following parameter description "ALMPARAM" , using the exact spelling and case.

## How to Import Parameter Data from a Database

VuGen enables you to import data from a database for use with parameterization. You can import the data in one of the following ways. After you import the data, it is saved as a file .dat extension with a prefix of the <source script name>\_ and stored as a regular parameter file.

### Create a Query Using Microsoft Query

1. In the "[Database Query Wizard](#)" on page 440, select **Create query using Microsoft Query**. If you need instructions on Microsoft Query, select **Show me how to use Microsoft Query**.
2. Click **Finish**. If Microsoft Query is not installed on your machine, VuGen issues a message indicating that it is not available. Install MS Query from Microsoft Office before proceeding.
3. Follow the instructions in the wizard, importing the desired tables and columns.
4. When you finish importing the data, select **Exit and return to the Virtual User Generator** and click **Finish**. The database records appear in the Parameter Properties box as a data file.

### Specify an SQL Statement Manually

1. In the "[Database Query Wizard](#)" on page 440, select **Specify SQL Statement Manually** and click **Next**.
2. Click **Create** to specify a new connection string. The Select Data Source window opens.

3. Select a data source, or click **New** to create a new one. The wizard guides you through the procedure for creating an ODBC data source. When you are finished, the connection string appears in the **Connection String** box.
4. In the **SQLstatement** box, enter an SQL statement.
5. Click **Finish** to process the SQL statement and import the data. The database records appears in the Parameter Properties box as a data file.

## Select or Create Parameter Dialog Box

This dialog box enables you to create a new parameter or modify an existing parameter.

	
<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• VuGen &gt; Solution Explorer pane &gt; right-click on the <b>Parameters</b> node &gt; <b>Create New Parameter</b></li><li>• In script editor, right-click on the value &gt; <b>Replace with Parameter</b> &gt; <b>Create New Parameter</b></li><li>• VuGen &gt; Design &gt; Parameters &gt; <b>Create New Parameter</b></li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Create a Parameter" on page 412</a>


User interface elements are described below:

UI Element	Description
<b>Parameter name</b>	The name of the parameter. <b>Note:</b> Do not use the name <b>unique</b> , it is used by VuGen.
<b>Parameter type</b>	The type of the parameter. For information about the different parameter types see <a href="#">"Parameter Types" on page 410</a> .
<b>Original value</b>	The original value of the parameter before parameterization.

<a href="#">Properties...</a>	Opens the Parameter Properties dialog box. For details, see "Parameter Properties Dialog Box" below.
-------------------------------	--

## Parameter Properties Dialog Box

This page allows you to view and modify the properties of a parameter. This dialog box varies depending on the type of parameter you are using.



To access [VuGen > Right-click parameter > Parameter properties](#)

### Date/Time, Group Name, Iteration Number, Load Generation Name, and Vuser ID Parameters

User interface elements are described below:

UI Element	Description
<a href="#">Add format -&gt;</a>	Adds the custom format specified in the <b>Date/time format</b> or <b>Text format</b> field to the format list.
<a href="#">Delete format &lt;-</a>	Deletes the selected format from the format list.
<a href="#">Reset formats</a>	Restores the format list to its default state.

UI Element	Description
Date/time format / Text format	You can specify a custom format here. See the chart below for a list of Date/time symbols.
Format list	The list of formats. See the chart below for a list of Date/time symbols.
Offset (Date/time to type only)	<p>Allows you to set an offset for the date/time parameter. For example, if you want to test a date next month, you set the date offset to 30 days.</p> <ul style="list-style-type: none"> <li><b>Working days only.</b> Use values for work days only (excludes Saturdays and Sundays).</li> </ul> <p><b>Note:</b> To change the non-working days, configure the NonWorkingDays parameter under the Misc section in the vugen.ini file:</p> <pre>[Misc] NonWorkingDays="5,6"</pre> <p>Days are represented by integers as follows:</p> <pre>Mon = 1, Tue = 2, Wed = 3 ,Thur = 4, Fri = 5, Sat = 6, Sun = 7</pre> <ul style="list-style-type: none"> <li><b>Prior to current date.</b> Sets the offset for a date or time that has already passed (negative offset).</li> </ul>
Parameter type	The parameter type. For more information see <a href="#">"Parameter Types" on page 410</a> .
Sample (current time)	Displays an example parameter value based on the selected format.







UI Element	Description
Update values on	<ul style="list-style-type: none"><li><b>Each occurrence.</b> Use a new value for each occurrence of the parameter in your script. This is useful when the statements using a parameter are unrelated. For example, for random data, it may be useful to use a new value for each occurrence of the parameter.</li><li><b>Each iteration.</b> Updates the parameter one time per iteration. If a parameter appears in a script several times, the Vuser uses the same value for all occurrences of the parameter, for the entire iteration. This is useful when the statements using a parameter are related.</li></ul> <p><b>Note:</b> If you create an action block with parameters using its own iteration count—if you instruct VuGen to update their values each iteration, it refers to the global iteration and not the block iteration.</p> <ul style="list-style-type: none"><li><b>Once.</b> Updates the parameter value only once during the scenario run. The Vuser uses the same parameter value for all occurrences and all iterations of the parameter. This type may be useful when working with dates and times.</li></ul>

The following table describes the date/time symbols:

Symbol	Description
c	complete date and time in digits
#c	complete date as a string and time
H	hours (24 hour clock)
I	hours (12 hour clock)
M	minutes
S	seconds
p	AM or PM
d	day
m	month in digits (01-12)
b	month as a string - short format (e.g. Dec)
B	month as a string - long format (e.g. December)
y	year in short format (e.g. 03)
Y	year in long format (e.g. 2013)

## File Parameters

User interface elements are described below:


UI Element	Description
	Adds a column to the data set.
	Adds a row to the data set.
	Creates a new data table.
	Opens the Database Query Wizard, enabling you to import data from an existing database. For more information, see <a href="#">"Importing Data" on page 434</a> .
	Deletes a column from the data set.
	Deletes a row from the data set.
	Enables you to view and edit parameter values in Notepad. This is important when working with large data sets because VuGen only displays up to 100 rows in the UI. Notepad opens with the parameter's name in the first row and its original value in the second row. Enter additional column names and values into the file using a delimiter such as a comma or a tab to indicate a column break. Begin a new line for each table row (for each new row of data). 
	Opens the Parameter Simulation dialog box. This allows you to simulate the parameter behavior with your data set. For more information, see <a href="#">"Parameter Simulation Dialog Box" on page 435</a> .
<b>Select Column</b>	Enables you to select the column to use as the data source either by the column <b>number</b> or <b>name</b> .
<b>File Format</b>	<ul style="list-style-type: none"> <li><b>Column delimiter.</b> The character used to separate values in the data file.</li> <li><b>First data line.</b> The first line of data to be used during Vuser script execution. The header is line 0. To begin with the first line after the header, specify 1. If there is no header, specify 0.</li> </ul>

UI Element	Description
<b>Select next row</b>	The method of selecting the file data during Vuser script execution. The options are: <b>Sequential</b> , <b>Random</b> , or <b>Unique</b> . For more information see " <a href="#">Data Assignment Methods for File/Table/XML Parameters</a> " on page 413.
<b>Update value on</b>	The method that determines when the parameter will switch to the next value. The choices are <b>Each Iteration</b> , <b>Each Occurrence</b> , and <b>Once</b> . For more information see " <a href="#">Data Assignment Methods for File/Table/XML Parameters</a> " on page 413.
<b>When out of values</b>	Specify what to do when there is no more unique data: <b>Abort the Vuser</b> , <b>Continue in a cyclic manner</b> , or <b>Continue with last value</b> .
<b>Allocate Vuser values in the Controller</b>	(LoadRunner only). Indicate whether you want to manually allocate data blocks for the Vusers. You can allow the Controller to automatically allocate a block size or you can specify the desired number of values. Select <b>Automatically allocate block size</b> or <b>Allocate x values for each Vuser</b> . For the second option, specify the number of values to allocate. To track this occurrence, enable the <b>Extended Log &gt; Parameter Substitution</b> option in the Log Run-Time settings. When there is not enough data, VuGen writes a warning message to the Vuser log "No more unique values for this parameter in table <table_name>".
<b>File path</b>	Select the .dat file with the data for your parameter. Alternatively, you can create a new data set using the <b>Create Table</b> button.

## Table Parameters

User interface elements are described below:

UI Element (A-Z)	Description
 <b>Add Column...</b>	Adds a column to the data set.
 <b>Add Row...</b>	Adds a row to the data set.
 <b>Create Table</b>	Creates a new data table.
 <b>Data Wizard...</b>	Opens the Database Query Wizard, enabling you to import data from an existing database. For more information, see
 <b>Delete Column...</b>	Deletes a column from the data set.
 <b>Delete Row...</b>	Deletes a row from the data set.

UI Element (A-Z)	Description
<b>Edit with Notepad...</b>	<p>Enables you to view and edit parameter values in Notepad. This is important when working with large data sets because VuGen only displays up to 100 rows in the UI.</p> <p>Notepad opens with the parameter's name in the first row and its original value in the second row. Enter additional column names and values into the file using a delimiter such as a comma or a tab to indicate a column break. Begin a new line for each table row (for each new row of data).</p> 
<b>Allocate Vuser values in the Controller</b>	<p>(LoadRunner only). Indicate whether you want to manually allocate data blocks for the Vusers. You can allow the Controller to automatically allocate a block size or you can specify the desired number of values. Select <b>Automatically allocate block size</b> or <b>Allocate x values for each Vuser</b>. For the second option, specify the number of values to allocate. To track this occurrence, enable the <b>Extended Log &gt; Parameter Substitution</b> option in the Log Run-Time settings. When there is not enough data, VuGen writes a warning message to the Vuser log "No more unique values for this parameter in table &lt;table_name&gt;".</p>
<b>Column</b>	<p>The columns to use. Alternatively, you can select <b>Select all columns</b>. To specify one or more columns by their number, select <b>Columns by number</b> and enter the column numbers separated by a comma or a dash. The column number is the index of the column containing your data. For example, if the data for the parameter is in the table's first column, select 1. In the <b>Column delimiter</b> box, select a column delimiter—the character used to separate the columns in the table. The available delimiters are: comma, tab, space.</p>
<b>File path</b>	<p>Select the .dat file with the data for your parameter. Alternatively, you can create a new data set using the <b>Create Table</b> button.</p>
<b>Row delimiter for log display</b>	<p>This delimiter is used to differentiate between rows in the output logs. If you enable parameter substitution logging, VuGen sends the substituted values to the Replay log. The row delimiter character in the Replay log indicates a new row.</p>

UI Element (A-Z)	Description
Rows	<ul style="list-style-type: none"> <li><b>Rows per iteration.</b> How many rows to use per iteration. This is only relevant when the <b>Update value on</b> field is set to <b>Each iteration</b>. If <b>Update value on</b> is set to <b>Once</b>, then the same rows will be used for all iterations.</li> <li><b>First line of data.</b> The first line of data to be used during script execution. To begin with the first line after the header, enter 1.</li> <li><b>Table information</b>. Displays information about the table, including how many rows of data are available.</li> </ul>
Select next row	The method of selecting the file data during Vuser script execution. The options are: <b>Sequential</b> , <b>Random</b> , or <b>Unique</b> . For more information see " <a href="#">Data Assignment Methods for File/Table/XML Parameters</a> " on page 413.
Update value on	The method that determines when the parameter will switch to the next value. The choices are <b>Each Iteration</b> , <b>Each Occurrence</b> , and <b>Once</b> . For more information see " <a href="#">Data Assignment Methods for File/Table/XML Parameters</a> " on page 413.
When not enough rows	Specifies what VuGen does when there are not enough rows in the table for the iteration. <b>Example:</b> The table you want to fill has 3 rows, but your data only has two rows. Select <b>Parameter will get less rows than required</b> to fill in only two rows. Select <b>Use behavior of "Select Next Row"</b> to loop around and get the next row according to the method specified in the <b>Select next row</b> box.
When out of values	Specify what to do when there is no more unique data: <b>Abort the Vuser</b> , <b>Continue in a cyclic manner</b> , or <b>Continue with last value</b> .

## Random Number Parameters

User interface elements are described below:

UI Element	Description
Number format	Specifies the minimum number of digits your parameter will have. Where <b>%01d</b> represents one digit, <b>%02d</b> represents two digits, and so on.
Random range	The minimum and maximum range for the random values.
Sample value	Displays an example parameter value based on the selected format.

UI Element	Description
Update value on	<ul style="list-style-type: none"><li><b>Each occurrence.</b> Use a new value for each occurrence of the parameter in your script. This is useful when the statements using a parameter are unrelated. For example, for random data, it may be useful to use a new value for each occurrence of the parameter.</li><li><b>Each iteration.</b> Updates the parameter one time per iteration. If a parameter appears in a script several times, the Vuser uses the same value for all occurrences of the parameter, for the entire iteration. This is useful when the statements using a parameter are related.</li></ul> <p><b>Note:</b> If you create an action block with parameters using its own iteration count—if you instruct VuGen to update their values each iteration, it refers to the global iteration and not the block iteration.</p> <ul style="list-style-type: none"><li><b>Once.</b> Updates the parameter value only once during the scenario run. The Vuser uses the same parameter value for all occurrences and all iterations of the parameter. This type may be useful when working with dates and times.</li></ul>

## Unique Number Parameters

**Note:** When scheduling a scenario in the Controller, the **When out of values** option only applies to the **Run for HH:MM:SS** option in the Schedule Builder's Duration tab. It is ignored for the **Run until completion** option.

User interface elements are described below:

UI Element	Description
Number format	Specifies the minimum number of digits your parameter will have. Where <b>%01d</b> represents one digit, <b>%02d</b> represents two digits, and so on.
Number range	<ul style="list-style-type: none"><li><b>Start.</b> The starting value.</li><li><b>Block size per Vuser.</b> The amount of unique numbers assigned to each Vuser. For example, if you specify a starting value of 1 and a block size of 100, the values 1-100 can be used by the first Vuser, the values 101-200 can be used by the second Vuser, and so on.</li></ul>
Sample value	Displays an example parameter value based on the selected format.

UI Element	Description
Update value on	<ul style="list-style-type: none"> <li><b>Each occurrence.</b> Use a new value for each occurrence of the parameter in your script. This is useful when the statements using a parameter are unrelated. For example, for random data, it may be useful to use a new value for each occurrence of the parameter.</li> <li><b>Each iteration.</b> Updates the parameter one time per iteration. If a parameter appears in a script several times, the Vuser uses the same value for all occurrences of the parameter, for the entire iteration. This is useful when the statements using a parameter are related.</li> </ul> <p><b>Note:</b> If you create an action block with parameters using its own iteration count—if you instruct VuGen to update their values each iteration, it refers to the global iteration and not the block iteration.</p> <ul style="list-style-type: none"> <li><b>Once.</b> Updates the parameter value only once during the scenario run. The Vuser uses the same parameter value for all occurrences and all iterations of the parameter. This type may be useful when working with dates and times.</li> </ul>
When out of values	<p>Determines what to do when the range of values is reached for a Vuser. The range of values is determined by the start value and the block size.</p> <p><b>Abort Vuser.</b> Terminates the Vuser script.</p> <p><b>Continue in a cyclical manner.</b> Restart the unique numbers for this Vuser from the beginning of its assigned range. For example, if a Vuser had the range of 1-100 and it reached 100, it would start again at 1.</p> <p><b>Continue with last value.</b> Use the last assigned value for this parameter for all subsequent occurrences of this parameter. For example, if a Vuser had the range of 1-100 and it reached 100, it would continue with the value of 100 until the end of the script.</p>

## User Defined Function Parameters

User interface elements are described below:

UI Element	Description
Function Name	The name of the function. Use the name of the function as it appears in the DLL file.
Library Names	The location of the relevant library files.

UI Element	Description
Update value on	<ul style="list-style-type: none"><li><b>Each occurrence.</b> Use a new value for each occurrence of the parameter in your script. This is useful when the statements using a parameter are unrelated. For example, for random data, it may be useful to use a new value for each occurrence of the parameter.</li><li><b>Each iteration.</b> Updates the parameter one time per iteration. If a parameter appears in a script several times, the Vuser uses the same value for all occurrences of the parameter, for the entire iteration. This is useful when the statements using a parameter are related.</li></ul> <p><b>Note:</b> If you create an action block with parameters using its own iteration count—if you instruct VuGen to update their values each iteration, it refers to the global iteration and not the block iteration.</p> <ul style="list-style-type: none"><li><b>Once.</b> Updates the parameter value only once during the scenario run. The Vuser uses the same parameter value for all occurrences and all iterations of the parameter. This type may be useful when working with dates and times.</li></ul>

## XML Parameters

For information about Web Services XML parameters, see ["XML Parameters" on page 416](#).

## Parameter Simulation Dialog Box

This dialog box allows you to view a simulation of the behavior of a file parameter.

To access	VuGen > Parameter List > Select Parameter > Simulate Parameter
-----------	--

<b>Important information</b>	<ul style="list-style-type: none"><li>• This feature is only relevant for file type parameters.</li><li>• Not all types of Parameter Substitution can be simulated. If you select <b>Select next row: Same line as...</b> or <b>Update value on: Each occurrence</b>, then the Parameter Simulation dialog box will not open.</li><li>• VuGen can simulate up to 256 iterations and 256 Vusers.</li><li>• <b>Run Indefinitely</b> is compliant with the <b>Real-life schedule</b> in the Scheduler of the Controller.</li><li>• If you select <b>Select next row: Unique</b> in the Parameter List dialog, then each Vuser is assigned a unique range of rows from which the Simulator will substitute values (for that Vuser).</li></ul> <p><b>Note:</b> If you have more than one unique parameter, you need to verify that each parameter has defined values for all Vusers.</p> <p>With this setting, the default selection in the Allocate Vuser values in the Controller section is <b>Automatically allocate block size</b>. In this case, when you run the simulation, the range allocation takes place in accordance with your Scenario run mode selection. If you change the default selection to <b>Allocate x values for each Vuser</b>, then the Vusers will be allocated the amount of values you specify, ignoring of your Scenario run mode selection.</p>
------------------------------	--

User interface elements are described below:

UI Element	Description
<b>Vusers</b>	The number of Vusers to run in the simulation.
<b>Scenario Run Mode</b>	<ul style="list-style-type: none"><li>• <b>Run until completion.</b> Enter the number of iteration to run or select <b>Take number of iteration from Run-Time settings</b>.</li><li>• <b>Run indefinitely.</b> Simulates the run indefinitely option in the controller. VuGen only actually simulates the number of iterations you specify.</li></ul>
<b>Simulate</b>	Runs the parameter simulation. The values of each parameter substitution are displayed.

**Example:**


In the following examples, the settings in the Parameter List dialog box are:

- **Values for the new parameter.** Value1 to Value7
- **Select next row.** Unique

- **When out of rows.** Continue with last value
- **Allocate Vuser values in the Controller.** Automatically allocate block size

#### Scenario run mode: Run until completion

In the following example, the user has selected three Vusers, set the Scenario run mode to **Run until completion**, and selected three iterations.




When the scenario run mode is set to **Run until completion**, the number of rows that each Vuser receives is the same as the number of iterations. The range allocation stops when there are no longer enough rows in the table.

As the simulation is run, the first Vuser takes the first three values (because this was the number of iterations). The second Vuser takes the next three values. The third Vuser takes the remaining value in the first iteration. For the remaining iterations, since the **When out of values** option in the Parameter List dialog box was set to **Continue with last value**, the third Vuser continues with the same value.

A fourth Vuser would have failed.

#### Scenario run mode: Run indefinitely

In the following example, the user has selected 3 Vusers and set the Scenario run mode to Run indefinitely and selected to show 3 iterations.



When the Scenario run mode is set to Run indefinitely, the allocated range for each Vuser is calculated by dividing the number of cells in the .dat file by the number of Vusers. In this scenario, that is  $7/3 = 2$  (The simulator takes the closest smaller integer.).

As the simulation is run, the first Vuser takes Value1 and Value2. The second Vuser takes Value3 and Value4 and the third Vuser takes Value5 and Value6. Since there were only 3 Vusers, Value7 was not distributed.

**Note:** If you hold the mouse over the cells in the first column of the table, a tool tip appears with information about which values were assigned to that Vuser.

If you hold the mouse over cells which were not assigned values, a tool tip appears with the reason no values were assigned.


A tool tip does not appear if a proper value was assigned.

## Parameter List Dialog Box

This dialog box enables you to view, create, delete, select, and modify parameters. The Parameter list shows all of the parameters that you created, including both input and output parameters.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• VuGen &gt; Solution Explorer pane &gt; &gt; Parameters node &gt; Parameter List</li><li>• In the script editor, right-click on a value &gt; Replace with Parameter&gt; Parameter List</li><li>• VuGen &gt; Design &gt; Parameters &gt; Parameter List</li></ul>
<b>Important information</b>	Do not name a parameter <i>unique</i> , since this name is used by VuGen.
<b>See also</b>	<a href="#">"Parameter Properties Dialog Box" on page 426</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 New	Creates a new parameter. This does not replace any highlighted text with the parameter. Do not name a parameter <i>unique</i> , since this name is used by VuGen.
 Delete	Deletes the selected parameter. <b>Note:</b> If the parameter replaced a previous value, the original value is restored.

<b>&lt;Parameter Properties Pane&gt;</b>	This pane appears different depending on the type of parameter you are using. For information about this pane, see one of the following sections: <ul style="list-style-type: none"> <li>For Date/Time, Group Name, Iteration Number, Load Generation Name, and Vuser ID parameters see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For File parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For Table parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For BPT parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For Random Number parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For Unique Number parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For User Defined Function parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> <li>For XML parameters, see "<a href="#">Parameter Properties Dialog Box</a>" on page 426.</li> </ul>
<b>Parameter type</b>	This drop-down list lets you select the parameter type. For information about the different parameter types, see " <a href="#">Parameter Types</a> " on page 410.

## Database Query Wizard

This wizard enables you to select data for a parameter from an existing database.

<b>To access</b>	<b>VuGen &gt; Right-click parameter &gt; Parameter properties &gt; Data Wizard (only available for File / Table type parameters)</b>
<b>Relevant tasks</b>	<a href="#">"How to Import Parameter Data from a Database" on page 424</a>

User interface elements are described below:

UI Element	Description
<b>Query Definition</b>	Select from one of the following options: <ul style="list-style-type: none"> <li>Create query using Microsoft Query</li> <li>Specify SQL statement manually</li> </ul>
<b>Show me how to use Microsoft Query</b>	Displays instructions for using Microsoft Query when after you click next.
<b>Maximum number of rows</b>	The maximum number of rows to be created in the .dat file based on the specified query.

## Create Parameter Dialog Box (Winsock)

This dialog box enables you to correlate data and create parameters in Winsock scripts.

To access	VuGen > Step Navigator > Right-click menu > Create Parameter
-----------	--

User interface elements are described below:

UI Element	Description
Parameter Name	The name of the parameter.
Data Range	You can define the parameter by a start and end range in bytes. Enter the numbers manually in the <b>From</b> and <b>To</b> fields or click <b>Select Range</b> and highlight the desired text.
Boundaries	You can define the parameter by defining a left and right boundary. To do so, select <b>Extract parameter data using boundaries</b> . Click the button to right of the <b>Left</b> field, highlight the desired text, and click <b>Done</b> . Repeat the procedure for the <b>Right</b> boundary.
Script Statement	The statement that will appear in your script based on the options selected in this dialog box. You can manually edit this statement.

## Parameter Original Value Dialog Box

This dialog box appears when you are parameterizing a Vuser script, and lets you specify the parameter's original value.

To access	In VuGen, select a text string in the Editor. Right-click and then select <b>Replace with Parameter &gt; Parameter List</b> . Select an existing parameter and click <b>Close</b> .
Important information	Each parameter has an original value. You can replace any parameter in a Vuser script with the parameter's original value. When you parameterize a selected text string and the selected text string is not the same as the selected parameter's original value, you can select to either keep the parameter's existing original value, or replace the parameter's original value with the selected text string.

User interface elements are described below:

UI Element	Description
Use old original value <text>	Keeps the parameter's existing original value.
Use new original value <text>	Assigns the selected text as the parameter's new original value.

# Parameters - Troubleshooting and Limitations

This section describes troubleshooting and limitations for parameters.

## Function Argument Limitations

You can use parameterization only for the arguments within a function. You cannot parameterize text strings that are not function arguments. In addition, not all function arguments can be parameterized. For details on which arguments you can parameterize, see the Function Reference ([Help > Function Reference](#)) for each function.

For example, consider the **Ird\_stmt** function. The function has the following syntax:

```
Ird_stmt (LRD_CURSOR FAR *mpCursor, char FAR *mpcText, long mliTextLen, LRDOS_I  
NT4 mjOpt1, LRDOS_INT4 mjOpt2, int miDBErrorSeverity);
```

The indicates that you can parameterize only the *mpcText* argument.

A recorded **Ird\_stmt** function could look like this:

```
Ird_stmt(Csr4, "select name from sysobjects where name =\"Kim\" ", -1, 148, -999  
99, 0);
```

You could parameterize the recorded function to look like this:

```
Ird_stmt(Csr4, "select name from sysobjects where name =\"<name>\" ", -1, 148, -  
99999, 0);
```

**Note:** You can use the **Ir\_eval\_string** function to "parameterize" a function argument that you cannot parameterize by using standard parameterization. In addition, you can use the **Ir\_eval\_string** function to "parameterize" any string in a Vuser script.

For VB, COM, and Microsoft .NET protocols, you must use the **Ir.eval\_string** function to define a parameter. For example,  
`Ir.eval_string("{Custom_param}")`.

For more information on the **Ir\_eval\_string** function, see the Function Reference.

## Data Table File Size Limitations

If .dat file's size is over 100MB, a message is displayed that the file is too big and will not be displayed.

If you need to load a file over 100MB, you can change "MaxParametersDisplaySize" parameter in *vugen.ini*:

```
[ParamTable]  
MaxParametersDisplaySize=100000000
```

# Async Studio

## Synchronous and Asynchronous Concepts

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

Original web applications communicated using conversations that had a synchronous nature. A typical synchronous conversation includes the following steps:

1. The user interacts with an application that is presented in a web browser.
2. Based on the user input, the browser submits a request to the web server.
3. The server sends a response to the request, and the application in the browser is updated.

Synchronous applications have a number of limitations. One limitation involves the updating of the data that is displayed in the application inside the browser. For example, consider an application that displays stock prices of a number of shares. Ideally, the application should be able to update the display of the stock prices as soon as the prices are updated on the web-server. A synchronous application would be able to update the prices on a fixed time interval. For example, every 10 seconds, the browser could send a request to the server for the most up-to-date stock prices. One limitation of this solution is that the displayed stock prices may be out-of-date for a period of time before the refresh interval is reached. Although this may not be critical in our share portfolio scenario, the scenario illustrates the limitation of a synchronous application to timely update information.

Where necessary, synchronous applications are being replaced with what are known as **asynchronous** applications. Asynchronous applications enable a client to be notified whenever an event occurs on the server side. Asynchronous applications are therefore better able to update information as required.

In order to enable asynchronous behavior, asynchronous communication occurs in parallel (simultaneously) with the main, synchronous flow of the business processes. This behavior makes asynchronous applications harder to accurately emulate using traditional synchronous Vuser scripts.

Although there are numerous types of asynchronous applications, there are three primary types: *push*, *poll*, and *long-poll*. For details, see "[Types of Asynchronous Communication](#)" below.

For an introduction to using asynchronous communication in Vuser scripts, see "[LoadRunner Support for Asynchronous Communication - Overview](#)" on page 446.

## Types of Asynchronous Communication


**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

### Asynchronous request and response sequences

Asynchronous communication is comprised of various request and response sequences. Such request and response sequences can be classified as one of three types of asynchronous communication: *poll*, *push*, and *long-poll*. When you develop a Vuser script, it is often useful to know the types of asynchronous communication that are implemented when the required business processes are performed.


### Polling Asynchronous Communication

The browser sends HTTP requests to the server at regular intervals, for example, every 5 seconds. The server responds with updates. This enables the system to intermittently update the application interface inside the browser. If the server has no update, it informs the application that there is no update, based on the application protocol.



### Long-Polling Asynchronous Communication


The client generates an HTTP request to a known address on the server. Whenever the server has an update, it responds with an HTTP response. Immediately after receiving the server response, the client issues another request.



### Push Asynchronous Communication

The client opens a connection with the server by sending a single HTTP request to a known address on the server. The server then sends a response that appears to never end, so that the client never closes the connection. Whenever necessary, the server sends a "sub message" update to the client over the open connection. The server may or may not terminate this connection. During the time the connection is open, if the server has no real update to send, it sends "ping" messages to the client to prevent the client from closing the connection for timeout reasons.

Note that push-type conversations are supported for Web (HTTP/HTML) protocol actions inside Web (HTTP/HTML), Flex, Silverlight, and Web Services Vuser scripts, NOT for **Flex\_amf\_call** steps in Flex Vuser scripts.



## LoadRunner Support for Asynchronous Communication - Overview

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

Web-based applications can exhibit synchronous behavior, asynchronous behavior, or a combination of both. For an introduction to these behavior types, see ["Synchronous and Asynchronous Concepts" on page 443](#). LoadRunner enables you to build and run Vuser scripts that emulate user activity for both synchronous and asynchronous applications. To build a Vuser script for a synchronous application, follow the typical LoadRunner Vuser script building process. However, to build a script for an asynchronous application, you must perform some additional tasks - beyond the typical LoadRunner Vuser script building process. If you record and generate a script for an application that performs asynchronous behavior - without performing the additional asynchronous-related tasks, the script may not run successfully.

Building a Vuser script for an asynchronous application begins with recording the business processes that produce the asynchronous communication. After the business processes are recorded and the Vuser script is generated, VuGen scans the generated Vuser script and attempts to locate the asynchronous communication. If asynchronous communication is detected, VuGen modifies the script - inserting the appropriate asynchronous API functions.

## Identifying Asynchronous Conversations

In order for VuGen to be able to successfully identify the asynchronous behavior in a Vuser script, the asynchronous communication must contain at least the required minimum number of request and response sequences.

- Identifying a poll-type conversation

To enable VuGen to successfully identify a poll conversation, the recorded Vuser script must contain at least 3 sequences with matching URLs and similar polling intervals.

- Identifying a long-poll type conversation

To enable VuGen to successfully identify a long-poll conversation, the recorded Vuser script must contain at least 3 sequences with matching URLs.

**Note:** VuGen will scan a script for asynchronous communication only if the **Async Scan** recording option is selected. For details, see "[How to Create an Asynchronous Vuser Script](#)" on the next page.

In some scenarios, the modifications that VuGen makes to the Vuser script are sufficient to enable the script to run and emulate the required asynchronous behavior. In other scenarios, additional "manual" modifications are required. For details, see "[How VuGen Modifies a Vuser Script for Asynchronous Communication](#)" on page 451.

**Note:** the modifications that must be made to a generated Vuser script to enable the script to emulate asynchronous behavior are dependent on the type of the asynchronous behavior: *push*, *polling*, or *long-polling*. For details, see "[Types of Asynchronous Communication](#)" on page 443.

Asynchronous communication in a Vuser script is divided into one or more conversations. The individual asynchronous conversations that VuGen detects in a Vuser script are listed in the **Async** tab of the **Design Studio**. Use this list of asynchronous conversations to systematically analyze the modifications that VuGen made to the Vuser script to make sure that VuGen has correctly identified the asynchronous behavior, and correctly modified the Vuser script to emulate the required asynchronous behavior. For details on the **Async** tab of the **Design Studio**, see "[Async Tab \[Design Studio\]](#)" on page 471.

After modifying a Vuser script to enable it to emulate asynchronous communication, it may be necessary to perform correlation activities on the modified script. For details about correlation, see "[Correlating Asynchronous Vuser Scripts](#)" on page 459.

**Note:** Async functionality is not supported when you replay a Vuser script in WinINet mode.

For details on how to build a Vuser script for an application that utilizes asynchronous communication, see "[How to Create an Asynchronous Vuser Script](#)" on the next page.

# How to Create an Asynchronous Vuser Script

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

To build a Vuser script for an asynchronous application, perform the following:

## Create a new Vuser script

1. Click the **New Script** button on the VuGen toolbar.
2. Select **Web - HTTP/HTML**, or one of the other Vuser protocols that support asynchronous communication.
3. Click **Create**. VuGen creates a basic Vuser script.

## Enable Async Scan

1. Select **Record > Recording Options**.
2. Under **General**, select **Code Generation**.
3. Make sure that the **Async Scan** check box is selected. This instructs VuGen to scan the Vuser script after recording, locate asynchronous communication, and insert the appropriate asynchronous functionality.

## Record the business processes using the typical VuGen recording process

1. Click **Record** on the VuGen toolbar.
2. Enter the required information in the Start Recording dialog box, and then click **Start Recording**.
3. Perform the business processes that the Vuser will emulate, and then click **Stop Recording** on the floating toolbar.

Note that in order for VuGen to be able to successfully identify the asynchronous behavior in a Vuser script, the asynchronous communication must contain at least the required minimum number of client requests and server responses. For details, see "[Types of Asynchronous Communication](#)" on page 443.

## Generate, scan, and modify the Vuser script

1. After you click **Stop Recording**, VuGen generates the Vuser script.

2. After generating the script, VuGen scans the generated script to locate instances of asynchronous communication.
3. If VuGen locates any instances of asynchronous communication, VuGen will modify the script to enable the script to run and emulate the asynchronous behavior. For details, see "[How VuGen Modifies a Vuser Script for Asynchronous Communication](#)" on page 451.
4. The **Design Studio** opens. Click the **Async** tab. The **Async** tab displays a list of all instances of asynchronous communication that VuGen located in the Vuser script.

## Review the modifications that VuGen made to the script

For each asynchronous conversation that appears in the **Async** tab of the **Design Studio**, perform the following tasks:

1. Open the Vuser script in the Editor.
2. Locate the **web\_reg\_async\_attributes** step that starts the asynchronous conversation. Ensure that the **web\_reg\_async\_attributes** step is located at the start of the asynchronous conversation.
3. Make sure that the URL parameter in the **web\_reg\_async\_attributes** step is the same as one of the URLs that are specified in the action step that follows the **web\_reg\_async\_attributes** step.

For details on the **web\_reg\_async\_attributes** step, see "[Defining the Start of an Asynchronous Conversation](#)" on page 454.

4. Notice that the step comment before the **web\_reg\_async\_attributes** step contains a TODO token. The TODO token indicates that you should check the relevant callback implementations in the AsyncCallbacks.c extra file.
5. Locate the **web\_stop\_async** step that ends the asynchronous conversation. Ensure that the **web\_stop\_async** step is located at the end of the asynchronous conversation.
6. Make sure that the **web\_stop\_async** step runs as required. For details, see "[Fine-Tuning the End of an Asynchronous Conversation](#)" on page 458.

For details on the **web\_stop\_async** step, see "[Defining the End of an Asynchronous Conversation](#)" on page 456.

7. Review the callback implementation and make modifications to the script as required. For details, see "[Implementing Callbacks](#)" on page 459.
8. Make sure that all *counter* and *complex string* parameters are set correctly. Notice that for each such parameter, a TODO comment exists and has a matching task in the **Tasks** pane. For details, see "[Parsing URLs](#)" on page 466.
9. Check the **Tasks** pane for specific actions that are required in order to complete the script development process. Such actions may include verifying callback implementations, or

verifying the implementation of specific parameters.

10. Once all parameters are initialized correctly, run the script to make sure that the asynchronous conversation runs as expected.

**Note:** Async functionality is not supported when you replay a Vuser script in WinINet mode.

Once you have reviewed the modified script and made sure that the asynchronous communication has been implemented correctly, run the script. For details, see [Enabling Asynchronous Scripts to Run](#).

## Asynchronous Communication API

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

The LoadRunner API includes several functions that enable Vuser scripts to emulate asynchronous communication. These asynchronous communication functions are:

### **web\_reg\_async\_attributes**

This function registers the next action function as the beginning of an asynchronous conversation, and defines the behavior of the asynchronous communication.

### **web\_stop\_async**

This function cancels the specified asynchronous conversation, including all its active and future tasks.

### **web\_sync**

This function suspends the Vuser script execution until the specified parameter is defined.

### **web\_util\_set\_request\_url**

This function sets the specified string to be the request URL for the next request sent in the conversation. This is applicable only when called from a callback.

### **web\_util\_set\_request\_body**

This function sets the specified string to be the request body for the next request sent in the conversation. This is applicable only when called from a callback.

### **web\_util\_set\_formatted\_request\_body**

This function is similar to the **web\_util\_set\_request\_body** function. However, this function is included as part of a Flex protocol asynchronous conversation instead of a Web(HTTP/HTML) protocol asynchronous conversation. This function expects an XML formatted request body, which will be converted before the request is sent.

For details on the asynchronous API functions, see the Function Reference (**Help > Function Reference**).

The **web\_reg\_async\_attributes** function should be called before the step that starts the asynchronous conversation. The **web\_reg\_async\_attributes** function receives a number of arguments that define the asynchronous conversation. One of these arguments is the URL of the asynchronous conversation. As soon as the replay engine downloads this URL in the step that follows the **web\_reg\_async\_attributes** function, the asynchronous conversation begins. The callbacks that are registered in the **web\_reg\_async\_attributes** function enable the script developer to control some of the characteristics of the asynchronous conversation (for example, to change the URL). The asynchronous conversation continues until the **web\_stop\_async** step, or until the end of the iteration. In a push-type conversation, the server may close the connection and thereby end the conversation.

**Note:** Async functionality is not supported when you replay a Vuser script in WinINet mode.

For details on how the asynchronous functions differ from synchronous functions, see "[How Asynchronous Functions Differ from Synchronous Functions](#)" below.

## How Asynchronous Functions Differ from Synchronous Functions

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

The LoadRunner API includes several functions that enable Vuser scripts to emulate asynchronous communication. These asynchronous functions differ from the other API functions in the following ways:

1. The network traffic that the asynchronous functions generate runs in parallel – simultaneously – with the main flow in the Vuser script. This means that the asynchronous communication can continue even when the synchronous steps end.
2. The asynchronous communication continues even during execution of non-web functions (e.g. **lr\_think\_time**).
3. Some of the asynchronous communication API functions use callback functions. The user needs to specify callbacks that are scheduled by the replay engine when a predefined event occurs. For details on using callbacks with asynchronous functions, see "[Implementing Callbacks](#)" on page 459.

## How VuGen Modifies a Vuser Script for Asynchronous Communication

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After you create a Vuser script and record the required business processes, VuGen generates the Vuser script. VuGen then scans the generated script to locate instances of asynchronous communication. This process is called an Async scan. If VuGen locates any instances of asynchronous communication in the Vuser script, VuGen modifies the script to enable the script to run and emulate the required asynchronous behavior.

**Note:** VuGen will scan a script for asynchronous communication only if the **Async Scan** recording option is selected. For details, see "[How to Create an Asynchronous Vuser Script](#)" on page 448.

Asynchronous communication in a Vuser script is divided into one or more conversations. The individual asynchronous conversations that VuGen detects in a Vuser script are listed in the **Async** tab of the **Design Studio**. Use this list of asynchronous conversations to systematically analyze the modifications that VuGen made to the Vuser script during the Async scan. Make sure that VuGen has correctly identified the asynchronous behavior in the Vuser script, and correctly modified the Vuser script to emulate the required asynchronous behavior. For details on the **Async** tab of the **Design Studio**, see "[Async Tab \[Design Studio\]](#)" on page 471.

**Note:** After modifying a Vuser script to enable it to emulate asynchronous communication, it may be necessary to perform correlation activities on the modified script. For details about correlation, see "[Correlating Asynchronous Vuser Scripts](#)" on page 459.

How does VuGen modify a Vuser script?

Asynchronous behavior in a Vuser script is divided into one or more asynchronous conversations. For each asynchronous conversation, VuGen performs the following tasks:

1. VuGen inserts a **web\_reg\_async\_attributes** step before the start of the asynchronous conversation. The **web\_reg\_async\_attributes** step includes an ID for the asynchronous conversation. This ID is used by a subsequent **web\_stop\_async** step to indicate the end of the asynchronous conversation. The Pattern argument indicates the type of the asynchronous behavior: *push*, *poll*, or *long-poll*.

```
web_reg_async_attributes("ID=Push_0",
    "Pattern=Push",
    "URL=http://push.example.com/example",
    "RequestCB=Push_0_RequestCB",
    "ResponseHeadersCB=Push_0_ResponseHeadersCB",
    "ResponseBodyBufferCB=Push_0_ResponseBodyBufferCB",
    "ResponseCB=Push_0_ResponseCB",
```

LAST);

For details on how a **web\_reg\_async\_attributes** step is used at the start of an asynchronous conversation, see "[Defining the Start of an Asynchronous Conversation](#)" on the next page.

For details on the **web\_reg\_async\_attributes** function, see the Function Reference (**Help > Function Reference**).

For details on the types of asynchronous behavior that are supported by LoadRunner, see "[Types of Asynchronous Communication](#)" on page 443.

2. VuGen adds a comment before the inserted **web\_reg\_async\_attributes** step. The comment includes details about the asynchronous conversation, including:
  - a. The ID of the asynchronous conversation.
  - b. The URLs that are included in the conversation.
  - c. Suggested implementations for the callback functions that are declared in the **web\_reg\_async\_attributes** step. These implementations are added in AsyncCallbacks.c, one of the script's extra files.

```
/* Added by Async CodeGen.

ID=Push_0

ScanType = Recording

The following URLs are considered part of this conversation:

http://push.example.com/example

TODO - The following callbacks have been added to AsyncCallbacks.c.

Add your code to the callback implementations as necessary.

Push_0_RequestCB

Push_0_ResponseHeadersCB

Push_0_ResponseBodyBufferCB

Push_0_ResponseCB

*/
```

3. For *push* conversations, VuGen inserts asynchronous API functions into the Vuser script, but

does not remove any of the recorded code from the Vuser script. For *polling* and *long-polling* conversations, VuGen may remove steps or step parameters from the generated Vuser script. VuGen removes steps or step parameters in cases where the relevant URLs will be requested by running the inserted asynchronous functions - and not by running the original steps that have been removed.

**Note:** Removed steps are not deleted – they are commented out. You can "uncomment" these steps if required.

4. When relevant, VuGen adds a **web\_stop\_async** step at the end of the asynchronous conversation. The **web\_stop\_async** step marks the end of the asynchronous conversation. For details on the **web\_stop\_async** step, see the Function Reference ([Help > Function Reference](#)).
5. The recording snapshots are updated by grouping the tasks in the asynchronous conversation under the step that started the conversation.

### How VuGen modifies **flex\_amf\_call** steps

VuGen supports asynchronous polling and long-polling behavior in **flex\_amf\_call** steps. Flex scripts that contain *polling* or *long-polling* in **flex\_amf\_call** steps are handled by VuGen just like Web(HTTP/HTML) scripts, except for the following:

- The RequestCB will contain a commented call to **web\_util\_set\_formatted\_request\_body**, which can be used to pass an XML formatted request body, which will be encoded and sent with the request.
- The **aResponseBodyStr** and **aResponseBodyLen** parameters of the ResponseCB give user access to the XML representation of the response body.

## Defining the Start of an Asynchronous Conversation

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After VuGen scans a Vuser script for asynchronous communication, the Async tab of the Design Studio lists the asynchronous conversations that VuGen found in the script. VuGen inserts a **web\_reg\_async\_attributes** into the Vuser script at the start of each asynchronous conversation that was detected. Use VuGen's Step Navigator to find the associated **web\_reg\_async\_attributes** steps in the Vuser script. The **web\_reg\_async\_attributes** steps should be located where the asynchronous conversations start when the script runs.

A **web\_reg\_async\_attributes** step that is added to a Vuser script includes the following parameters:

- ID
- URL
- Pattern
- PollIntervalMS (for poll-type conversations only)
- RequestCB
- ResponseBodyBufferCB (for push-type conversations only)
- ResponseHeadersCB (for push-type conversations only)
- ResponseCB

The URL parameter in the **web\_reg\_async\_attributes** step should be the same as one of the URLs that are specified in the step that follows the **web\_reg\_async\_attributes** step. For details on the **web\_reg\_async\_attributes** step, see the Function Reference ([Help > Function Reference](#)).

#### Inserting a Comment

When VuGen inserts a **web\_reg\_async\_attributes** step into a script, VuGen inserts an associated comment before the **web\_reg\_async\_attributes** step. The inserted comment contains information about the associated asynchronous conversation, such as the conversation ID, the communication pattern (*push*, *poll*, or *long-poll*), a list of URLs that are part of the asynchronous communication, and list of callbacks implemented in the AsyncCallbacks.c extra file.

Notice that the step comment contains a TODO token. The TODO token indicates that you should check the relevant callback implementations in the AsyncCallbacks.c extra file.

For details on how an asynchronous conversation is terminated, see "[Defining the End of an Asynchronous Conversation](#)" on the next page.

#### Example - **web\_reg\_async\_attributes**

The sample code below shows a **web\_reg\_async\_attributes** step that was added by VuGen. Notice that the **web\_reg\_async\_attributes** step was added before a **web\_url** step, and that the URL parameter in the **web\_reg\_async\_attributes** step is the same as the URL parameter in the **web\_url** step.

```
/* Added by Async CodeGen.
ID=Poll_0
ScanType = Recording

The following urls are considered part of this conversation:
http://your URL.com/content.php?messages

TODO - The following callbacks have been added to AsyncCallbacks.c.
Add your code to the callback implementations as necessary.
    Poll_0_RequestCB
    Poll_0_ResponseCB
*/
    web_reg_async_attributes("ID=Poll_0",
        "URL=http://your URL.com/content.php?messages",
        "Pattern=Poll",
        "RequestCB=Poll_0_RequestCB",
        "ResponseCB=Poll_0_ResponseCB",
        LAST);

    web_url("content.php",
        "URL=http://your URL.com/content.php?messages",
        "Resource=0",
        "RecContentType=text/xml",
        "Referer=http://your URL.com/",
        "Snapshot=t2.inf",
        "Node=HTML",
        LAST);
```

## Defining the End of an Asynchronous Conversation

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After VuGen scans a Vuser script for asynchronous communication, the Async tab of the Design Studio lists the asynchronous conversations that VuGen found in the script. A **web\_stop\_async** step is inserted into the Vuser script at the end of each asynchronous conversation that was detected. Use VuGen's Step Navigator to find the associated **web\_stop\_async** steps in the Vuser script.

**Note:** In some cases VuGen will not add a **web\_stop\_async** step at the end of an asynchronous conversation. This may occur when VuGen is not able to determine where the asynchronous conversation ends. This can occur when the asynchronous conversation was added due to a specific Async rule or when the asynchronous conversation was not ended during the recording. For details on Async rules, see "["Async Rules - Overview" on page 468](#)".

After VuGen has inserted a **web\_stop\_async** step into a Vuser script, make sure the **web\_stop\_async** step was added in the correct location in the script, that is – where the asynchronous conversation should end when the Vuser script runs.

In order to make sure the asynchronous conversation ends correctly when the script runs, it may be necessary to modify the details of the **web\_stop\_async** step in the Vuser script. For details, see "["Fine-Tuning the End of an Asynchronous Conversation" on page 458](#)".

**Note:** All Async conversations are automatically terminated at the end of each iteration even if the **Simulate a new user each iteration** run-time option is disabled.

For details on how an asynchronous conversation is started, see "[Defining the Start of an Asynchronous Conversation](#)" on page [454](#).

**Example - web\_stop\_async:**

In the code sample below, VuGen added a **web\_stop\_async** step at the end of a *poll* conversation. In this example, the original polling steps are commented out, and the **lr\_think\_time** steps that separated them have been merged into one **lr\_think\_time** step in order to emulate the duration of the entire *poll* conversation.

```
/* Removed by Async CodeGen.
ID = Poll_0
*/
/*
web_url("content.php_7",
    "URL=http://your_URL.com/content.php?messages",
    "Resource=0",
    "RecContentType=text/xml",
    "Referer=http://your_URL.com/",
    "Snapshot=t8.inf",
    "Mode=HTML",
    LAST);
*/

lr_think_time(24);

web_stop_async("ID=Poll_0",
    LAST);
```

## Using Asynchronous Request Thresholds

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

You can fine-tune some of VuGen's behavior when VuGen scans a Vuser script to locate asynchronous communication. You use VuGen's asynchronous request thresholds to fine-tune VuGen's behavior. Each of the thresholds is associated with only one of the types of asynchronous conversations: *push*, *poll*, or *long-poll*.

- **Asynchronous request thresholds for push conversations**

**Minimum Response Size.** Specify the minimum response content length (in bytes) for defining *push* asynchronous conversations. If the server sent less than the specified value, VuGen will not classify the conversation as a push-type asynchronous conversation.

**Maximum Sub Message Size.** Specify the maximum sub message size (in bytes) sent by the server for defining *push* asynchronous conversations. If the server sent a sub message of size greater than the specified value, VuGen will not classify the conversation as a push-type asynchronous conversation.

**Minimum Number of Sub Messages.** Specify the minimum number of sub messages for defining *push* asynchronous conversations. A push conversation in which less than the specified number of sub messages was sent by the server will not be classified by VuGen as a push-type asynchronous conversation.

- **Asynchronous request thresholds for poll conversations**

**Interval Tolerance.** Specify the interval tolerance (in milliseconds) for classifying *poll* asynchronous conversations. A conversation in which intervals differ from each other by more than the specified value will not be classified by VuGen as a poll-type asynchronous conversation.

- **Asynchronous request thresholds for long-poll conversations**

**Maximum Interval.** Specify the maximum interval (in milliseconds) between the end of one response and the start of a new request for classifying *long-poll* asynchronous conversations. A conversation in which a request starts more than the specified value after the end of the previous response will not be classified by VuGen as a long-poll type asynchronous conversation.

For details on the available asynchronous request thresholds, see "[Asynchronous Options Dialog Box](#)" on page 473.

## Fine-Tuning the End of an Asynchronous Conversation

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After VuGen scans a Vuser script for asynchronous communication, the Async tab of the Design Studio lists the asynchronous conversations that were found in the script. A **web\_stop\_async** step is inserted into the Vuser script at the end of each asynchronous conversation that was detected. In order to make sure that each asynchronous conversation ends correctly when the script runs, it may be necessary to perform one or more of the following tasks:

- Remove the **web\_stop\_async** step so that the asynchronous conversation will be terminated at the end of the iteration.

- Move the **web\_stop\_async** step to a location that is after an existing action step or an existing **Ir\_think\_time** step, so the asynchronous conversation will end after that step is performed.
- Add an **Ir\_think\_time** step before the **web\_stop\_async** step, or change the time parameter in an existing **Ir\_think\_time** step. Make sure that think-time is enabled in the Run-Time Settings. For details, see "[General > Think Time Node](#)" on page 350.
- Add a **web\_sync** step to stop the asynchronous conversation after a specified parameter receives a value. Use the asynchronous conversation callbacks to make sure the parameter receives a value only when you want to end the conversation.

## Correlating Asynchronous Vuser Scripts

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After modifying a Vuser script to enable it to emulate asynchronous communication, it may be necessary to perform correlation activities on the modified script. Due to asynchronous nature, dynamic values from asynchronous communication cannot be handled by Design Studio, and must be correlated manually.

You can search for dynamic values inside Response callbacks functions using the **Ir\_save\_param\_regexp** function. This function can be called from a callback to extract the necessary value from server response (**ResponseCB**) or response buffer (**ResponseBodyBufferCB**), and assign this value to a parameter. This parameter can then be used for correlations.

For details about the **Ir\_save\_param\_regexp** function, see the Function Reference ([Help > Function Reference](#)).

## Implementing Callbacks

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After VuGen scans a Vuser script for asynchronous communication, the **Async** tab of the **Design Studio** lists the asynchronous conversations that were found in the script. For each asynchronous conversation found during the scan, VuGen adds the callback function signatures matching those declared in the **web\_reg\_async\_attributes** step. The signatures are added to the `AsyncCallbacks.c` extra file.

The available callbacks are:

1. RequestCB

This callback is called before a request is sent.

2. ResponseBodyBufferCB

This callback is called when there is content in the response body buffer and at the end of the response body. This callback is generated by VuGen automatically for *push*-type conversations, but is available for *poll* and *long-poll* conversations as well.

### 3. ResponseCB

This callback is called after every response is received in the conversation.

- The names of the callback functions start with the conversation ID of the asynchronous conversation. For example, the RequestCB callback for an asynchronous conversation with ID "LongPoll\_0" will be **LongPoll\_0\_RequestCB**.
- The names of the callback functions are declared in the **web\_reg\_async\_attributes** step in the script.

#### Example 1:

In the following sample code, the three callback functions are declared in the **web\_reg\_async\_attributes** step.

```
/* Added by Async CodeGen.
ID=LongPoll_0
ScanType = Recording

The following urls are considered part of this conversation:
http://your URL.com/request.ashx?key=111111-11
http://your URL.com/request.ashx?key=111111-11
http://your URL.com/request.ashx?key=111111-11
http://your URL.com/request.ashx?key=111111-11

TODO - The following callbacks have been added to AsyncCallbacks.c.
Add your code to the callback implementations as necessary.
    LongPoll_0_RequestCB
    LongPoll_0_ResponseCB
*/
web_reg_async_attributes("ID=LongPoll_0",
    "URL= http://your URL.com/request.ashx?key=111111-11",
    "Pattern=LongPoll",
    "RequestCB=LongPoll_0_RequestCB",
    "ResponseCB=LongPoll_0_ResponseCB",
    LAST);
```

#### Example 2:

In the following sample code, the two callbacks are implemented in the AsyncCallbacks.c extra file.

```
int LongPoll_0_RequestCB()
{
    //enter your implementation for RequestCB() here

    //call web_util_set_request_url() here to modify polling url
    //web_util_set_request_url("<request_url>");

    //call web_util_set_request_body() here to modify request body:
    //web_util_set_request_body("<request body>");

    return WEB_ASYNC_CB_RC_OK;
}

int LongPoll_0_ResponseCB(
    const char *      aResponseHeadersStr,
    int               aResponseHeadersLen,
    const char *      aResponseBodyStr,
    int               aResponseBodyLen,
    int               aHttpStatusCode)
{
    //enter your implementation for ResponseCB() here

    return WEB_ASYNC_CB_RC_OK;
}
```

You can modify the callbacks to implement the required behavior. For details, see ["Modifying Callbacks" on the next page](#).

### Example 3:

The following sample code shows an implementation of the ResponseHeader callback function, including the three arguments: HTTP Status code, Accumulated headers string and Accumulated headers string length.

```
int Push_0_ResponseHeadersCB(
    int aHttpStatusCode,
    const char * aAccumulatedHeadersStr,
    int aAccumulatedHeadersLen)
{
    //Enter your implementation for ResponseHeadersCB() here.

    lr_output_message("Response status code is :[%d]", aHttpStatusCode);
    lr_output_message("Response headers are :/n[%s]", aAccumulatedHeadersStr);

    return WEB_ASYNC_CB_RC_OK;
}
```

```
}
```

A sample of the output from the above callback function is shown below:

```
Response status code is :[200]
Response headers are :
[HTTP/1.1 200 OK
Connection: close
Date: Tue, 25 Jun 2013 09:03:33 GMT
Server: Microsoft-IIS/6.0
Content-Type: text/html
Cache-control: private]
```

## Modifying Callbacks

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

After VuGen scans a Vuser script for asynchronous communication, the **Async** tab of the **Design Studio** lists the asynchronous conversations that were found in the script. For each asynchronous conversation found during the scan, VuGen adds the required callback function declarations in the **AsyncCallbacks.c** file. To implement the required behavior, you can modify the callbacks that were added by VuGen. Modifying a callback includes:

### Modifying the request URL in the RequestCB callback

In *poll* and *long-poll* conversations, requested URLs often change in each polling iteration. The change is usually determined by client-side logic, usually implemented by JavaScript that is executed by the browser. Parts of the URL may be determined by correlation of a known parameter, such as a session ID. For details, see ["Parsing URLs" on page 466](#).

Request URLs in an asynchronous conversation will be modified before the request is sent by using the RequestCB and the **web\_util\_set\_request\_url** function.

```
The following urls are considered part of this conversation:
http://www.example.com/example.aspx?message=helloaaa&iteration=1&timestamp=1324389551431
http://www.example.com/example.aspx?message=hellobbb&iteration=2&timestamp=1324389555643
http://www.example.com/example.aspx?message=helloccc&iteration=3&timestamp=1324389558664
http://www.example.com/example.aspx?message=hellobbb&iteration=4&timestamp=1324389560113
```

## Modifying the request body in the RequestCB callback

The request body in requests that are part of an asynchronous conversation may need to be modified before the request is sent. You use the RequestCB and the `web_util_set_request_body` util function to modify the request body.

Modifying the request body is useful in *poll* and *long-poll* conversations in which each new request requires a different request body.

```
//an example of a parametrized request body sent in the RequestCB.  
//the value of {request_body} may be set in the callback function,  
//or elsewhere in the script.|  
web_util_set_request_body("{request_body}");
```

Each RequestCB that is generated by VuGen contains a commented snippet. You can "uncomment" the snippet in order to use the `web_util_set_request_body` util function.

If VuGen finds that different requests have different body values in the recorded conversation, the generated RequestCB will contain a comment that prompts you to check the recording in order to implement the request body sent in each request when the script runs.

```
//call web_util_set_request_body() here to modify request body:  
//web_util_set_request_body("<request body>");  
//TODO - use snapshot view to see examples of request bodies sent|
```

## Modifying the response in the ResponseCB callback

You can modify the response callback in an asynchronous conversation to verify validity of the responses, or to wait for a specific event. For example, you could check the response headers for each response to determine if a specific value was received.

```
int Poll_0_ResponseCB(  
    const char *    aResponseHeadersStr,  
    int             aResponseHeadersLen,  
    const char *    aResponseBodyStr,  
    int             aResponseBodyLen,  
    int             aHttpStatusCode)
```

When the expected value has been received, you can use a `web_stop_async` step in the Action file to end the asynchronous conversation.

The following code sample provides an example for ending a synchronized conversation. In this example, in the **AsyncCallback.c** file, the script counts 10 iterations of the polling conversation, after which it creates a new parameter, **stopAsync**.

```
int Poll_0_ResponseCB()
{
    ...
    //increment iteration counter for every response received.
    static int iter = 0;
    iter++;

    //Once the desired number of responses has been reached,
    //create and save the parameter.
    if (iter > 10) {
        lr_save_int(iter, "stopAsync");
    }
    return WEB_ASYNC_CB_RC_OK;
}
```

In the Action file, the **web\_sync** step uses the generated parameter, **stopAsync**, to end the conversation:

```
web_reg_async_attributes("ID=Poll_0","Pattern=Poll",
    "URL=http://pumpkin:2080/nioamfpoll;AMFSessionId=6F8D6108-E309-38B2-3D65-963B4
31D0A38",
    "PollIntervalMs=3000",
    "RequestCB=Poll_0_RequestCB",
    "ResponseCB=Poll_0_ResponseCB",
    LAST);

web_custom_request("nioamfpoll;AMFSessionId=6F8D6108-E309-38B2-3D65-963B431D0A3
8_2",
    "URL=http://pumpkin:2080/nioamfpoll;AMFSessionId=6F8D6108-E309-38B2-3D65-963B4
31D0A38",
    "Method=POST",
    "Resource=0",
    "RecContentType=application/x-amf",
    "Referer=http://pumpkin:8081/lcds-samples/traderdesktop/traderdesktop.swf/[[DY
NAMIC]]/3",
    "Snapshot=t11.inf",
    "Mode=HTML",
    "EncType=application/x-amf",
    "BodyBinary=\x00\x03\x00\x00\x00\x01\x00\x04null\x00\x02/6\x00\x00
\x00Z\n\x00\x00\x00\x01\x11\n\x07\x07DSC\x8D\x02\n\x0B\x01\x01\x06
\x01\x05\tDSId\x06I6F8D611E-DC1C-9D0C-2BBA-36CC2AB8633B\x01\x0C!\xC0\xB
E\xA6Z74\xBE\xC3\xCF\xC7\xFA\xE6\xC3\t\xE2\x92\x01\x06\x01\x01\x01\x0
4\x02",
    LAST);

lr_think_time(30);
```

```
//suspend the script until the desired number
//of iterations have been performed.
web_sync("ParamCreated=stopAsync", "RetryIntervalMs=1000", "RetryTimeoutMs=30000
0", LAST);

web_stop_async("ID=Poll_0",LAST);
```

For more details about ending an asynchronous conversation, see ["Defining the End of an Asynchronous Conversation" on page 456](#).

## Modifying callbacks in Flex Vuser scripts

For Flex asynchronous *polling* and *long-polling* conversations, the generated RequestCB in the **AsyncCallback.c** file contains a call to `web_util_set_formatted_request_body`, which sets an XML formatted request body for each request.

```
web_util_set_formatted_request_body("<AMFPacket AMF_version=\"3\">"
    "<AMFHeaders />"
    "<Messages>"
        "<Message method=\"null\" target=\"/{Target_Poll_0}\">>"
        ...
    "</Message>"
    "</Messages>"
    "</AMFPacket>");
```

After uncommenting the commented code in the TODO section, and adding your callback code, open the Script Design Studio to scan for correlations.

Note that code generation automatically parameterizes the Target parameter in the request body. It also generates code for automatically incrementing this parameter before each polling iteration.

The generated RequestCB also contains a reminder to ensure that the counter initialization parameter for **Target\_Poll\_0** in the Action file matches the target attribute in the first *Message* element in the first polling request.

```
lr_param_increment("Target_Poll_0", "{Target_Poll_0}");

web_util_set_formatted_request_body("<AMFPacket AMF_version=\"3\">"
    "<AMFHeaders />"
    "<Messages>"
        "<Message method=\"null\" target=\"/{Target_Poll_0}\">>"
        ...
    "</Message>"
    "</Messages>"
    "</AMFPacket>");
```

In the Action file, make sure that you initialize the same polling parameter used in **AsyncCallbacks.c**. In the following segment from the Action file, the polling parameter, *Target\_Poll\_0*, matches the one used in **AsyncCallbacks.c**.

```
/* Initialize target parameter before sending first request. */
/* Notice that parameter will be incremented once before first request. */
lr_save_int(5, "Target_Poll_0");
```

For more details on using callback functions, see "["Implementing Callbacks" on page 459.](#)

## Parsing URLs

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

URLs that are included in asynchronous conversations often include query strings that are derived in a variety of ways. These strings may include:

- Time-stamps
- Counters
- Complex strings

To enable a Vuser script to successfully perform asynchronous communication, VuGen must be able to recreate the required URLs.

- When the URL includes a time-stamp, VuGen is usually able to successfully create the required URL.
- When the URL includes a counter, VuGen is usually able to recreate the counter, but it may be necessary to manually initialize the counter in the script.
- When the URL includes more complex strings, the algorithms for generating the URLs must be manually added to the code in the Vuser script.

### Example:

The sample code below shows a set of URLs that are part of a *long-poll* conversation. The URLs are included in the comment generated for a **web\_reg\_async\_attributes** step:

```
The following urls are considered part of this conversation:  
http://www.example.com/example.aspx?message=helloaaa&iteration=1&timestamp=1324389551431  
http://www.example.com/example.aspx?message=hellobbb&iteration=2&timestamp=1324389555643  
http://www.example.com/example.aspx?message=helloccc&iteration=3&timestamp=1324389558664  
http://www.example.com/example.aspx?message=helioddd&iteration=4&timestamp=1324389560113
```

If none of the parameters shown in the code sample above was found in VuGen's scan of the recorded Vuser script, the RequestCB implementation will contain a snippet that may be uncommented in order to set the URL for each response according to user defined code. For details, see "["Modifying Callbacks" on page 462.](#)

```
//call web_util_set_request_url() here to modify request url:  
//web_util_set_request_url("<request url>");
```

If any or all of the parameters shown in the sample code above are found during VuGen's scan of the recorded Vuser script, the RequestCB implementation will contain the following:

- A comment prompting the user to call **web\_util\_set\_request\_url**. The comment will contain a parameterized version of the URL.
- For each *time-stamp* parameter found in the URL, a snippet for saving the time-stamp to a parameter.
- For each *counter* parameter found in the URL, a snippet for incrementing a counter parameter. A matching step for initializing the counter parameter will also be added to the Action file. The snippet will also contain examples of the URL token containing the counter parameter, as seen during the recording.
- For each *complex string* parameter found in the URL, a snippet for saving the string to a parameter. It is up to the user to generate the correct string to be saved to the parameter to be used in the URL. The snippet will also contain examples of the URL token that is considered an unknown parameter, as seen during the recording.
- A snippet for passing the parameterized version of the URL to the **web\_util\_set\_request\_url** function.

Example: A snippet containing the parameterized version of a URL.

```
//call web_util_set_request_url() here to modify polling url  
//url is expected to be of the form:  
//http://www.example.com/example.aspx?message={Unknown\_LongPoll\_0\_0}  
//&iteration={Counter_LongPoll_0_1}&timestep={TimeStamp_LongPoll_0_2}
```

Example: A snippet prompting the user to set the value of an unknown parameter.

```
//TODO - implement parameter of type unknown: Unknown_LongPoll_0_0.  
//Known examples for Unknown_LongPoll_0_0:  
//message=[{"channel":"/meta/connect","connectionType":"long-polling","id":3,"clientId":"113fc44"}],  
//message=[{"channel":"/meta/connect","connectionType":"long-polling","id":5,"clientId":"113fc44"}],  
//message=[{"channel":"/meta/connect","connectionType":"long-polling","id":6,"clientId":"113fc44"}],  
//message=[{"channel":"/meta/connect","connectionType":"long-polling","id":7,"clientId":"113fc44"}].  
lr_save_string("[{\\"channel\\":\"\\\\\\\\meta\\\\connect\\\", \"connectionType\\\":\"long-polling\\\", \"id\\\":3, \"clientId\\\":\"113fc44.\"}],  
\"Unknown_LongPoll_0_0");
```

Example: A snippet for incrementing a counter parameter.

```
//TODO - check counter initialization for Counter_LongPoll_0_1 in Action file.  
//Known examples for the token containing Counter_LongPoll_0_1:  
//iteration=1, iteration=2, iteration=3, iteration=4 gPoll_0_1:  
lr_param_increment("Counter_LongPoll_0_1", "{Counter_LongPoll_0_1}");
```

Example: A snippet for initializing a counter parameter.

```
lr_save_int(0, "Counter_LongPoll_0_1");
```

Example: A snippet for saving a timestamp parameter.

```
web_save_timestamp_param("TimeStamp_LongPoll_0_2", LAST);
```

Example: A snippet for passing the parameterized version of a URL to the `web_util_set_request_url` function.

```
//once all parameters have been assigned, copy them to the updated url,  
//and call web_util_set_request_url() with the updated url:  
web_util_set_request_url("http://www.example.com/example.aspx?message={Unknown_LongPoll_0_0}  
&iteration={Counter_LongPoll_0_1}&timestamp={TimeStamp_LongPoll_0_2}");
```

## Async Rules - Overview

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

In some cases, when VuGen performs an Async scan, VuGen may fail to correctly identify some of the asynchronous conversations that are included in the Vuser script. In other cases, VuGen may erroneously classify regular synchronous steps as part of asynchronous conversations. To help rectify both of these scenarios, you can define Async rules to determine how requests to specified URLs are classified during an Async scan.

Async rules can be positive or negative.

- **Positive:** When VuGen fails to identify asynchronous conversations that are included in a Vuser script, implement a positive Async rule to enable VuGen to identify the asynchronous behavior.

Scenario: VuGen does not identify URLs under **http://www.true-async.com/push\_example.aspx** as push asynchronous conversations, and you know that they are part of push asynchronous conversations. Add a positive rule to enable VuGen to correctly identify the push asynchronous conversations. When you regenerate the script, the Async scan will apply the added rule, and all URLs that start with **http://www.true-async.com/push\_example.aspx** will be included as part of push asynchronous conversations.

- **Negative:** When VuGen erroneously classifies regular synchronous steps as part of an asynchronous conversation, implement a negative Async rule to prevent VuGen from erroneously identifying asynchronous behavior.

Scenario: VuGen identifies all URLs under **http://www.not-async.com/** as asynchronous poll conversations. You know that these are not asynchronous conversations. Implement a negative Async rule to prevent VuGen from erroneously identifying asynchronous behavior. When you regenerate the script, the Async scan will apply the added rule so that all URLs that start with **http://www.not-async.com/** will not be classified as part of asynchronous conversations.

For details on how to implement Async rules, see "[Adding Async Rules](#)" below.

## Adding Async Rules

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

When VuGen scans a Vuser script after recording or regenerating the script, VuGen may fail to identify asynchronous conversations that are included in the Vuser script. In other cases, VuGen may erroneously classify a regular synchronous step as part of an asynchronous conversation.

You can define Async rules that determine how requests to specified URLs will be classified during an Async scan. Async rules may be positive or negative. This topic describes how to implement Async rules. For an introduction to Async rules, see "[Async Rules - Overview](#)" on the previous page.

### Adding a positive Async rule

1. Select **Record > Recording Options > General > Code Generation** and then click **Async Options**. The Asynchronous Options dialog box opens.
2. Under **Asynchronous Regular Expressions**, click **Add Async Rule** . The Add Rule dialog box opens.
3. From the **Type** list, select **Push**, **Poll**, or **Long Poll**, as required.
4. In **URL Regular Expression**, enter a regular expression for URLs that should be considered part of asynchronous conversations.

## Special characters that you can include in a regular expression:

. Any single character
* Zero or more
+ One or more
? Zero or one
^ Beginning of line
\$ End of line
\n Line break
\r Carriage return
[] Any one character in the set
[^] Any one character not in the set
\w Word character
\W Non-word character
\d Decimal digit
\D Non-decimal digit
Or
\ Escape special character

**Note:** To include characters such as "?" and "+" in the regular expression, insert a backslash "\ before the required character.

5. Click **OK**. The new rule appears in the list of Async rules for the Vuser script.

**Note:** When you regenerate the script:

- For each push conversation that includes a URL that matches the regular expression, VuGen inserts asynchronous API functions into the Vuser script, but does not remove any of the recorded code from the Vuser script.
- For each polling or long-polling conversation that includes a URL that matches the regular expression, VuGen inserts asynchronous API functions into the Vuser script, and may remove steps or step parameters from the generated Vuser script. VuGen removes steps or step parameters in cases where the relevant URLs will be requested by running the inserted asynchronous functions - and not by running the original steps that have been removed.

For further details, see "[How VuGen Modifies a Vuser Script for Asynchronous Communication](#)" on page 451.

### Adding a negative Async rule

1. Select **Record > Recording Options > General > Code Generation** and then click **Async Options**. The Asynchronous Options dialog box opens.
2. Under **Synchronous Regular Expressions**, click **Add Async Rule** . The **Add Asynchronous Rule** dialog box opens.
3. From the **Rule Type** list, select **Not Async**.
4. In **URL Regular Expression**, enter a regular expression for URLs that should not be considered part of asynchronous conversations.
5. Click **OK**. The new rule appears in the list of Async rules for the Vuser script.

When you regenerate the script, steps that contain URLs that match the regular expression will not be included in asynchronous conversations.

## Async Tab [Design Studio]

The Async tab of the Design Studio lists all the occurrences of asynchronous communication that VuGen detected in the Vuser script.

<b>To access</b>	<ul style="list-style-type: none"><li>• Select <b>Design &gt; Design Studio</b>, and then click the <b>Async</b> tab.</li><li>• Click the  <b>Design Studio</b> button on the VuGen toolbar, and then click the <b>Async</b> tab.</li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>• The <b>Design Studio</b> button is enabled only when you display a recorded Vuser script in the Solution Explorer.</li><li>• The Async tab enables you to only view the asynchronous communication that is included in the Vuser script - you cannot edit any of the asynchronous details from the Async tab. Changes to the asynchronous details must be made in the Vuser script.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Create an Asynchronous Vuser Script" on page 448</a>

User interface elements are described below:

UI Element	Description
Type	<p>Indicates the origin of the asynchronous code in the Vuser script:</p> <p><b>Record.</b> The asynchronous code was added by VuGen during an Async scan that was performed after recording or regenerating the Vuser script.</p> <p><b>Rule.</b> The asynchronous code was added by VuGen due to a specific rule in the Async rules file.</p> <p><b>Manual.</b> The asynchronous code was manually added by a user.</p>
Action	The section of the Vuser script in which the asynchronous behavior is located.
Occurrences	<ul style="list-style-type: none"> <li>For push-type conversations, <b>Occurrences</b> is always 1.</li> <li>For poll and long-poll conversations, <b>Occurrences</b> indicates the number of steps or extra resource attributes that were removed [commented-out] by VuGen during the Async scan of the Vuser script.</li> </ul>
Status	Always has the value <b>Applied</b> .
Async Type	The type of the asynchronous behavior that was detected: <b>Push</b> , <b>Poll</b> , or <b>Long-Poll</b> .
URL	The URL in the <b>web_reg_async_attributes</b> step that starts the asynchronous conversation.
Filter	Select which asynchronous conversations to display in the conversation list.
Details	Expands the dialog box to show details about the selected asynchronous conversation.
Name	Always has the value <b>web_reg_async_attributes</b> .
Line	The line in the Vuser script that contains the <b>web_reg_async_attributes</b> step.
Action Name	The section of the Vuser script in which the asynchronous behavior is located.
Description	The comment in the Vuser script that precedes the <b>web_reg_async_attributes</b> step.
Occurrences in Snapshot	<ul style="list-style-type: none"> <li>For push-type conversations, displays the response body.</li> <li>For poll and long-poll conversations, displays HTTP attributes associated with the asynchronous conversation.</li> </ul>
Options	Opens the Asynchronous Request Thresholds dialog box.

## Asynchronous Options Dialog Box

This dialog box enables you to fine-tune some of VuGen's behavior when VuGen scans a Vuser script to locate asynchronous communication.

To access	VuGen > Record > Recording Options > General > Code Generation and then click <b>Async Options</b> .
-----------	--

User interface elements are described below:

UI Element	Description
<b>Minimum Response Size</b>	Specify the minimum size (in bytes) of a server response for defining <i>push</i> asynchronous conversations. If the server sent less than the specified value, VuGen will not classify the conversation as a push-type asynchronous conversation.
<b>Maximum Sub Message Size</b>	Specify the maximum sub message size (in bytes) sent by the server for defining <i>push</i> asynchronous conversations. If the server sent a sub message of size greater than the specified value, VuGen will not classify the conversation as a push-type asynchronous conversation.
<b>Minimum Number of Sub Messages</b>	Specify the minimum number of valid sub messages for defining <i>push</i> asynchronous conversations. A push conversation in which less than the specified number of valid sub messages was sent by the server will not be classified by VuGen as a push-type asynchronous conversation.
<b>Interval Tolerance</b>	Specify the interval tolerance (in milliseconds) for classifying <i>poll</i> asynchronous conversations. A conversation in which intervals differ from each other by more than the specified value will not be classified by VuGen as a poll-type asynchronous conversation.
<b>Maximum Interval</b>	Specify the maximum interval (in milliseconds) between the end of one response and the start of a new request for classifying <i>long poll</i> asynchronous conversations. A conversation in which a request starts more than the specified value after the end of the previous response will not be classified by VuGen as a long-poll type asynchronous conversation.
Asynchronous Rules table	
<b>Rule Type</b>	<b>Push, Poll, and Long Poll</b> are positive asynchronous rules. <b>Not Async</b> is a negative rule. For details on the asynchronous rule types, see " <a href="#">"Async Rules - Overview"</a> on page 468.
<b>Regular Expression</b>	A regular expression for URLs that should be considered part of asynchronous conversations. For a list of the special characters that you can include in a regular expression, see " <a href="#">"Adding Async Rules"</a> on page 469.

## Asynchronous Example - Poll

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

The following example describes a Vuser script that includes a poll asynchronous conversation. The application that is emulated by the Vuser is a demo of a “wiki” page. The browser displays the wiki page, and sends requests to refresh the page at intervals of 5 seconds.

```
Action()
{
    web_url("wiki",
        "URL=http://example.com/",
        "Resource=0",
        "RecContentType=text/html",
        "Referer=",
        "Snapshot=t1.inf",
        "Mode=HTML",
        LAST);

    web_url("content.php",
        "URL=http://example.com/content.php?messages",
        "Resource=0",
        "RecContentType=text/xml",
        "Referer=http://example.com/",
        "Snapshot=t2.inf",
        "Mode=HTML",
        LAST);

    lr_think_time(4);

    web_url("content.php_2",
        "URL=http://example.com/content.php?messages",
        "Resource=0", http://example.com/content.php?messages",
        "RecContentType=text/xml",
        "Referer=http://example.com/",
        "Snapshot=t3.inf",
        "Mode=HTML",
        LAST);

    lr_think_time(4);

    web_url("content.php_3",
        "URL=http://example.com/content.php?messages",
        "Resource=0",
        "RecContentType=text/xml",
        "Referer=http://example.com/",
        "Snapshot=t4.inf",
        "Mode=HTML",
        LAST);
}
```

**Note:** You can modify VuGen's asynchronous request thresholds to assist VuGen in finding poll-type conversations. For details, see ["Using Asynchronous Request Thresholds" on page](#)

457.

The above script was generated by VuGen after the required business processes were recorded. An asynchronous scan was not performed on the script after the script was generated. Notice that the script contains a series of **web\_url** functions with a repeating URL, namely:

**http://example.com/content.php?messages**. These **web\_url** functions are separated by **Ir\_think\_time** functions, indicating that the **web\_url** functions repeat at intervals of 4 seconds.

When the Vuser script runs, requests for **http://example.com/content.php?messages** should be sent repeatedly until the script is finished. Additionally, these requests should be sent in parallel (simultaneously) with other actions performed in the Vuser script.

After VuGen performed an asynchronous scan on the script, the script looks as follows:

```
/* Added by Async CodeGen.
ID=Poll_0
ScanType = Recording

The following urls are considered part of this conversation:
http://example.com/content.php?messages

TODO - The following callbacks have been added to AsyncCallbacks.c.
Add your code to the callback implementations as necessary.
    Poll_0_RequestCB
    Poll_0_ResponseCB
*/
web_reg_async_attributes("ID=Poll_0",
    "URL=http://example.com/content.php?messages",
    "Pattern=Poll",
    "PollIntervalMs=4000",
    "RequestCB=Poll_0_RequestCB",
    "ResponseCB=Poll_0_ResponseCB",
    LAST);

web_url("content.php",
    "URL=http://example.com/content.php?messages",
    "Resource=0",
    "ReContentType=text/html",
    "Referer=http://example.com",
    "Snapshot=t4.inf",
    "Mode=HTML",
    LAST);
```

Notice that a **web\_reg\_async\_attributes** function has been added to the script before the first **web\_url** function that calls **http://example.com/content.php?messages**.

Except for the first call to **http://example.com/content.php?messages**, all other **web\_url** functions that call the same URL have been commented-out by VuGen.

Notice that the **Ir\_think\_time** functions have been merged into one **Ir\_think\_time** function.

The Snapshot pane for the remaining **web\_url** function shows that the snapshots for the removed **web\_url** functions now have Origin = Polling, and that they start at intervals of 5 seconds.

Path	Origin	Start Time	Response Time [mse]
/content.php?messages	Primary	0:0:5.823	399
/content.php?messages	Polling	0:0:6.547	4000
/content.php?messages	Polling	0:0:12.719	4000
/content.php?messages	Polling	0:0:18.941	4000

Since the requests also have a response time, the think time in `lr_think_time` functions between the polling steps in the original script has been rounded down to 4 seconds.

## Asynchronous Example - Push

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

The following example describes a Vuser script that is developed to emulate a browser displaying an application that utilizes push-type asynchronous conversations. The application is a demo of a “stock quote” page. The browser shows the page with the stock values, and then sends a request and receives a response with updated stock values. The request remains open until it is closed by the user. For as long as the page is displayed, the server will continue to send sub-messages as part of the response - whenever the server has an update for the displayed stocks. Whenever such a sub-message is received by the client, the client displays the updated stock values.

**Note:** You can modify VuGen's asynchronous request thresholds to assist VuGen in finding push-type conversations. For details, see ["Using Asynchronous Request Thresholds" on page 457](#).

Name	Price	Time	Change	Bid Size	Bid	Ask	Ask Size	Min	Max	Ref.
Anduct	3.09	10:32:54	1.64	5000	3.09	3.1	35500	2.48	3.64	3.04
Ations Europe	17.92	10:33:05	11.37	86000	17.92	17.98	1000	12.8	19.33	16.09
Bagies Consulting	6.43	10:33:04	-10.57	4500	6.43	6.44	8500	5.74	8.64	7.19
BAY Corporation	3.2	10:32:03	-11.84	37500	3.2	3.21	63500	3.13	4.28	3.63
CON Consulting	6.8	10:33:05	-10.64	24000	6.8	6.83	51000	6.23	9.08	7.61
Corcor PLC	2.58	10:32:54	12.17	61000	2.58	2.59	42000	1.87	2.7	2.3
CVS Asia	13.48	10:33:06	-12.41	94500	13.45	13.48	11000	12.38	18.34	15.39
Datio PLC	5.81	10:33:00	9.41	42500	5.8	5.81	1500	4.4	6.34	5.31
Dentems	4.87	10:33:05	0.2	12000	4.86	4.87	35500	3.91	5.67	4.86
ELE Manufacturing	7.19	10:33:01	-5.51	13500	7.19	7.2	51000	6.25	9.09	7.61

If you attempt to run a script that calls a push url - without first performing an asynchronous scan - the replay will halt while waiting for the response to the highlighted request. After two minutes, VuGen will display an error similar to the following, in the Replay log:

```
Action.c(140): Error -27782: Timeout (120 seconds) exceeded while waiting to receive data for URL "http://push.example.com" [MsgId: MERR-27782]
```

The error indicates that the response never finished.

Regenerating the script with Async Scan enabled will create a script similar to the following:

```
/* Added by Async CodeGen.
ID=Push_0
ScanType = Recording

The following urls are considered part of this conversation:
http://push.example.com/STREAMING\_IN\_PROGRESS?LS\_session=S343716d5eb050c64T2253451&LS\_phase=4903&LS\_domain=lights,

TODO - The following callbacks have been added to AsyncCallbacks.c.
Add your code to the callback implementations as necessary.
Push_0_RequestCB
Push_0_ResponseBodyBufferCB
Push_0_ResponseCB
*/
web_reg_async_attributes("ID=Push_0",
    "URL=http://push.example.com/STREAMING\_IN\_PROGRESS?LS\_session=\(CorrelationParameter\)&LS\_phase=4903&LS\_domain",
    "Pattern=Push",
    "RequestCB=Push_0_RequestCB",
    "ResponseBodyBufferCB=Push_0_ResponseBodyBufferCB",
    "ResponseCB=Push_0_ResponseCB",
    LAST);

web_url("STREAMING_IN_PROGRESS",
    "URL=http://push.example.com/STREAMING\_IN\_PROGRESS?LS\_session=\(CorrelationParameter\)&LS\_phase=4903&LS\_domain",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=http://www.app.example.com/Gift\_StockListDemo\_Basic/lightstreamer/lsgenerator.html",
    "Snapshot=t13.inf",
    "Mode=HTML",
    LAST);

web_custom_request("control.js",
    "URL=http://push.example.com/lightstreamer/control.js",
    "Method=POST",
    "Resource=0",
    "RecContentType=text/plain",
    "Referer=http://push.example.com/ajax\_frame.html?phase=594&domain=example.com",
    "Snapshot=t14.inf",
    "Mode=HTML",
    "Body=LS_session=(CorrelationParameter)&LS_table=1&LS_win_phase=19&LS_req_phase=311&LS_op=add&LS_mode=MERGE&LS_id=item1",
    LAST);
/* Added by Async CodeGen.
ID = Push_0
*/
web_stop_async("ID=Push_0",
    LAST);

return 0;
}

}

Notice that a web_reg_async_attributes function has been added before the web_url function that starts the push conversation, and that a web_stop_async function has been added after the last action step in the script. The script will now run successfully. The push conversation will remain active – running in parallel with the other script functions – until the web_stop_async function, or until the end of the script is reached.
```

Note that during the Async scan, VuGen did not remove (comment-out) any of the generated code in the Vuser script.

## Asynchronous Example - Long-Poll

**Note:** This topic applies to Web (HTTP/HTML), Mobile Application - HTTP/HTML, Flex, and Web Services Vuser scripts.

The following example describes a Vuser script that emulates an application that implements a *long-poll* asynchronous conversation. The application is a demo of a “chat” page. A browser shows

the chat page, and sends a request that remains open until a new message is sent to the chat by another user. After such a message is sent:

- The response is finished.
- The new message is shown in the browser.
- The browser sends another request in order to listen for the next message sent to the chat.



**Note:** You can modify VuGen's asynchronous request thresholds to assist VuGen in finding long-poll type conversations. For details, see "[Using Asynchronous Request Thresholds](#)" on [page 457](#).

The following is the Vuser script that VuGen generated after recording the application - before an asynchronous scan was performed. The script contains a series of **web\_url** functions with similar URLs. Since new requests are sent as soon as the previous response is finished, no **lr\_think\_time** functions are added between the **web\_url** functions. This helps to indicate that this is a *long-poll* conversation and not a *poll* conversation.

When the Vuser script runs, requests to the chat application should be sent repeatedly every time a response from the chat application is finished. In addition, requests should be sent in parallel (simultaneously) with other actions performed in the script.

After VuGen performs an asynchronous scan on the script, the modified script looks as follows:

```
/* Added by Async CodeGen.
ID=LongPoll_0
ScanType = Recording

The following urls are considered part of this conversation:
http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%
http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%
http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%
http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%

TODO - The following callbacks have been added to AsyncCallbacks.c.
Add your code to the callback implementations as necessary.
    LongPoll_0_RequestCB
    LongPoll_0_ResponseCB
- */

web_reg_async_attributes("ID=LongPoll_0",
    "URL=http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%"
    "Pattern=LongPoll",
    "RequestCB=LongPoll_0_RequestCB",
    "ResponseCB=LongPoll_0_ResponseCB",
    LAST);

web_url("request.ashx_3",
    "URL=http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%"
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t4.inf",
    "Mode=HTML",
    LAST);

/* Removed by Async CodeGen.
ID = LongPoll_0
- */
/* http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%
web_url("request.ashx 4",
    "URL=http://example.com/request.ashx?key=111111-1111-1111-111111token=123488858&message=%5B%"
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t5.inf",
    "Mode=HTML",
    LAST);
- */

/* Removed by Async CodeGen.
```

Notice that a **web\_reg\_async\_attributes** function has been added before the first **web\_url** function that calls the chat application.

Except for the first call the chat application, all other **web\_url** functions that call similar URLs have been commented out.

A close look at the Snapshot pane for the remaining **web\_url** function shows that the snapshots for the removed steps now have origin = Polling. Notice that the response times vary greatly as the responses arrive only when another user has sent a chat message. This helps to indicate that this is a long-poll conversation, and not a poll conversation.

## Viewing Replay Results

The **Viewing Replay Results** section explains how to view and customize the results of a Vuser script replay.

## Viewing Replay Results - Overview

Creating a Vuser script includes the steps shown below. This topic provides an overview of the seventh step, viewing the results of the replay of a Vuser script.



To assist with debugging a Vuser script, you can view a report that summarizes the results of your script run. VuGen generates the report during the Vuser script execution and you view the report when script execution is complete.

The Test Results window displays all aspects of the test run and can include:

- A high-level results overview report (pass/fail status)
- The data used in all runs
- An expandable tree of the steps, specifying exactly where application failures occurred
- The exact locations in the script where failures occurred
- A still image of the state of your application at a particular step
- A movie clip of the state of your application at a particular step or of the entire test
- Detailed explanations of each step and checkpoint pass or failure, at each stage of the test

## Customizing the Test Results Display

Each result set is saved in a single **.xml** file (called **results.xml**). This **.xml** file stores information on each of the test result nodes in the display. The information in these nodes is used to dynamically create **.htm** files that are shown in the top-right pane of the Test Results window.

Each node in the run results tree is an element in the **results.xml** file. In addition, there are different elements that represent different types of information displayed in the test results. You can take test result information from the **.xml** file and use XSL to display the information you require in a customized format (either when printing from within the Test Results window, when displaying test results in your own customized results viewer, or when exporting the test results to an HTML file).

XSL provides you with the tools to describe exactly which test result information to display and exactly where and how to display, print or export it. Using a XSL editor, you can modify the **.css** and **.xsl** files in the results folder, to change the appearance of the report (fonts, colors, and so forth).

For example, in the **results.xml** file, one element tag contains the name of an action, and another element tag contains information on the time at which the run was performed. Using XSL, you could tell your customized editor that the action name should be displayed in a specific place on the page and in a bold green font, and that the time information should not be displayed at all.

## Connecting to Application Lifecycle Management from the Test Results Window

To manually submit defects to Application Lifecycle Management from the Test Results window, you must be connected to Application Lifecycle Management.

The connection process has two stages.

- First, you connect to a local or remote Application Lifecycle Management server. This server handles the connections between the Test Results and the Application Lifecycle Management project.
- Next, you log in and choose the project you want to access. The project stores tests and run session information for the application you are testing.

**Note:** Application Lifecycle Management projects are password protected, so you must provide a user name and a password.

For more information on connecting to an ALM project, see "[How to Work with Scripts in ALM Projects](#)" on page 164.

## How to Send Custom Information to the Report

In addition to the information sent automatically to the report, for Web Service Vusers, you can send information to the report using the message functions `lr_output_message` or `lr_error_message`.

For task details, see "[How to Insert Steps into a Script](#)" on page 406.

## How to Configure the Appearance of the Test Results Window

By default, the Test Results window has the same look and feel as the window, using the Microsoft Office 2003 theme. You can change the look and feel of the Test Results window, as required.

To change these settings, select **View > Window Theme** and select the desired theme.

**Note:** You can apply the Microsoft Windows XP theme to the Tests Results window only if your computer is set to use a Windows XP theme.

## How to Open the Test Results of a Specific Run

This task describes how to open the test results window for a specific run.

1. Select **File > Open** from within the Test Results window.
2. Select a script file to display the test results for that file and select the desired test result file. By default, result files for tests are stored in **<Script>\<ResultName>.xml**. If your script is stored in Application Lifecycle Management, see below.
3. Select a results set and click **Open**.

**Note:** Results files for earlier versions were saved with a **.qtp** file extension. In the Select Results File dialog box, only results files with an **.xml** extension are shown by default. To view results files with a **.qtp** extension in the Select Results File dialog box, select **Test Results (\*.qtp)** in the **Files of type** box.

## Select a Script Stored in Application Lifecycle Management

1. Click the **Application Lifecycle Management Connection** button  and connect to your Application Lifecycle Management project.
2. In the Open Test Results dialog box, enter the path of the folder that contains the results file for your test, or click the browse button to open the Open Test from ALM Project dialog box.
3. Select **DB Vuser** in the **Test Type** list.
4. Select the script whose test results you want to view, and click **OK**.
5. In the Open Test Results dialog box, highlight the test result set you want to view, and click **Open**. The Test Results window displays the selected test results.


## How to Find Steps in the Test Results

This task describes how to search the test results for steps of a particular type.

1. Select **Tools > Find** from within the Test Results window.
2. Select the type of step you wish to find. You can select multiple options.
3. Select **Up** or **Down** to indicate the direction of the search.
4. Select **Find Next** to find the next occurrence of the type of step you selected.

## Test Results Window

This window displays a report that summarizes the results of your script run.



<b>To access</b>	<ul style="list-style-type: none"> <li>• Opens automatically after running a script.</li> <li>• VuGen &gt; Replay &gt; Test Results...</li> </ul>
<b>Important information</b>	<ul style="list-style-type: none"> <li>You can configure the result settings from <b>Tools &gt; Options &gt; Scripting &gt; Replay</b>.</li> <li>The Test Results window can show results with up to 300 levels in the tree hierarchy. If you have results with more than 300 nested levels, you can view the entire report by manually opening the <b>results.xml</b> file.</li> </ul>

User interface elements are described below:


UI Element	Description
<b>Report Tree</b>	<p>A graphical representation of the test results located in a pane on the left of the window. You can collapse or expand a branch in the run results tree to change the level of detail that the tree displays.</p> <p>The icons next to the steps indicate the following information:</p> <ul style="list-style-type: none"> <li>✓ Indicates a step that succeeded.</li> <li>✗ Indicates a step that failed.</li> <li>! Indicates a warning, meaning that the step did not succeed, but it did not cause the test to fail.</li> <li>! ✗ Indicates a step that failed unexpectedly.</li> </ul> <p>You can expand and collapse all of the nodes from the <b>View</b> menu, or by clicking *.</p>

, continued

<b>Results Details Pane (Results Summary)</b>	Contains details of the test run which change depending on which part of the report tree you select. When you select the top node of the tree, the Result Details tab shows a summary of the results for your test. When you select a branch or step in the tree, the Result Details tab contains the details for that step. The Result Details tab may also include a still image of your application for the highlighted step. <ul style="list-style-type: none"><li>Iterations, actions, and steps that contain checkpoints are marked <b>Passed</b> or <b>Failed</b> in the right part of the Test Results window and are identified by icons in the tree pane.</li><li>Iterations, actions, and steps that ran successfully, but do not contain checkpoints, are marked <b>Done</b> in the right part of the Test Results window.</li></ul>
<b>Screen Recorder Tab</b>	Contains the movie associated with your test results. If there is no movie associated with your test results, the Screen Recorder tab contains the message: No movie is associated with the results.
	Opens the test results of a specific run. For more details, see " <a href="#">How to Open the Test Results of a Specific Run</a> " on page 481.
	Opens the Print dialog box, enabling you to print the test results. For more information, see " <a href="#">Print Dialog Box</a> " on the next page.
	Opens the Filters dialog box, enabling you to filter the test results. For more information, see " <a href="#">Filters Dialog Box</a> " below.
	Opens the Find dialog box, enabling you to search the test results for steps of a particular type. For more information, see " <a href="#">How to Find Steps in the Test Results</a> " on page 482.
	Searches the test results for the previous step matching the criteria in the Find dialog box.
	Searches the test results for the next step matching the criteria specified in the Find dialog box.
	Selects the previous node.
	Selects the next node.
	Opens the product documentation.

## Filters Dialog Box

This dialog box enables you to filter the test results in the test results window.




To access	"Test Results Window" on page 482 > View > Filters
-----------	--

User interface elements are described below:

UI Element	Description
Iterations	<ul style="list-style-type: none"><li><b>All.</b> Displays test results from all iterations.</li><li><b>From iteration X to Y.</b> Displays the test results from a specified range of test iterations.</li></ul>
Status	<ul style="list-style-type: none"><li><b>Fail.</b> Displays the results for the steps that failed.</li><li><b>Warning.</b> Displays the results for the steps with the status <b>Warning</b> (steps that did not pass, but did not cause the script to fail).</li><li><b>Pass.</b> Displays the results for the steps that passed.</li><li><b>Done.</b> Displays the results for the steps with the status <b>Done</b> (steps that were performed successfully but did not receive a pass, fail, or warning status).</li></ul>
Content	<ul style="list-style-type: none"><li><b>All.</b> Displays all steps from all nodes in the test.</li><li><b>Show only actions.</b> Displays the action nodes in the test (not the specific steps in the action nodes).</li></ul>

## Print Dialog Box

This dialog box enables you to print the test results.




To access     ["Test Results Window" on page 482 > File > Print](#)

User interface elements are described below:

UI Element	Description
Print range	<ul style="list-style-type: none"><li><b>All.</b> Prints the results for the entire script.</li><li><b>Selection.</b> Prints the results for the selected branch in the run results tree.</li></ul>
Copies	The number of copies to print.
Print format	<ul style="list-style-type: none"><li><b>Short.</b> Prints a summary line (when available) for each item in the run results tree. This option is available only if you the print range is set to <b>All</b>.</li><li><b>Detailed.</b> Prints all available information for each item in the run results tree, or for the selected branch.</li><li><b>User-defined XSL.</b> Enables you to browse to and select a customized .xsl file. You can create a customized .xsl file that specifies the information to be included in the printed report, and the way it should appear. For more information, see <a href="#">"Customizing the Test Results Display" on page 480</a>.</li></ul>

## Print Preview Dialog Box

This dialog box enables you to view a print preview of the test results.




To access	"Test Results Window" on page 482 > File > Print Preview
Important information	If some of the information is cut off in the preview, for example, if checkpoint names are too long to fit in the display, click the <b>Page Setup</b> button in the Print Preview window and change the page orientation from <b>Portrait</b> to <b>Landscape</b> .

User interface elements are described below:

UI Element	Description
Print range	<ul style="list-style-type: none"><li><b>All.</b> Prints the results for the entire script.</li><li><b>Selection.</b> Prints the results for the selected branch in the run results tree.</li></ul>
Print format	<ul style="list-style-type: none"><li><b>Short.</b> Prints a summary line (when available) for each item in the run results tree. This option is available only if you set the print range to <b>All</b>.</li><li><b>Detailed.</b> Prints all available information for each item in the run results tree, or for the selected branch.</li><li><b>User-defined XSL.</b> Enables you to browse to and select a customized .xsl file. You can create a customized .xsl file that specifies the information to be included in the printed report, and the way it should appear. For more information, see "Customizing the Test Results Display" on page 480.</li></ul>

## Export to HTML File Dialog Box

This dialog box enables you to export the test results to an HTML file. This enables you to view the results even if the Test Results Viewer environment is unavailable. For example, you can send the file containing the results in an e-mail to a third-party. You can select the type of report you want to export, and you can also create and export a customized report.



To access	"Test Results Window" on page 482 > File > Export to HTML File
Important Information	In Test Result reports, you can only use the Export to HTML file utility for scripts replayed in version 9.50 and later. To generate an HTML report for scripts created with earlier versions, run the script again in the 9.50 version (or later) of the product.

User interface elements are described below:

UI Element	Description
Export Range	<ul style="list-style-type: none"><li><b>All.</b> Exports the results for the entire script.</li><li><b>Selection.</b> Exports result information for the selected branch in the results tree.</li></ul>
Export Format	<ul style="list-style-type: none"><li><b>Short.</b> Prints a summary line (when available) for each item in the run results tree. This option is available only if you set the print range to All.</li><li><b>Detailed.</b> Prints all available information for each item in the run results tree, or for the selected branch.</li><li><b>User-defined XSL.</b> Enables you to browse to and select a customized .xsl file. You can create a customized .xsl file that specifies the information to be included in the printed report, and the way it should appear. For more information, see "Customizing the Test Results Display" on page 480.</li></ul>

## Protocols

### Protocol Support for Async, IPv6, and 64-bit Recording

The following table shows the protocol support for Async, IPv6, and 64-bit recording:

Protocol	Async	IPv6	64-bit recording
DNS	No	Yes	No
Flex AMF	Yes	Yes	No
Flex RMTP	No	No	No
FTP	No	Yes	No
IMAP	No	Yes	No
Java Over HTTP	No	Yes	Yes
LDAP	No	No	Yes
Microsoft .NET	No	No	Yes
Mobile Applications HTTP/HTML	No	Yes	No
Windows Sockets (multi-protocol)	No	Yes	Yes
Oracle 2-Tier	No	No	Yes
Oracle NCA	No	Yes	Yes
POP3	No	Yes	No
RDP	No	Yes	Yes
SAP – Web	No	No	Yes
Siebel - Web	No	No	Yes
Silverlight	No	Yes	No

Protocol	Async	IPv6	64-bit recording
SMTP	No	Yes	No
TruClient Ajax - FireFox	No	Yes	No
TruClient Ajax - IE	No	Yes	No
TruClient Ajax - Mobile	No	Yes	No
Click & Script family (Ajax, SAP)	No	Yes	No
Web - HTTP/HTML	Yes	Yes	Yes
Web Services	Yes	Yes	Yes

**Note:** In all the protocols that support asynchronous sessions, recording will only be applied to web\_\* steps.

## Ajax - Click & Script Protocol

Ajax (Asynchronous JavaScript and XML) represents a group of technologies for creating interactive Web applications. With Ajax, web pages exchange small packets of data with the server, instead of reloading an entire page. This reduces the amount of time that a user needs to wait when requesting data. It also increases the interactive capabilities and enhances the usability.

Using Ajax, developers can create fast Web pages using Javascript and asynchronous server requests. The requests can originate from user actions, timer events, or other predefined triggers.

Ajax components, also known as Ajax controls, are GUI based controls that use the Ajax technique—they send a request to the server when a trigger occurs.

For example, a popular Ajax control is a **Reorder List** control that lets you drag components to a desired position in a list. VuGen's support for Ajax implementation is based on Microsoft's ASP.NET Ajax Control Toolkit formerly known as Atlas.

## Ajax (Click & Script) Protocol Overview

Ajax (Asynchronous JavaScript and XML) represents a group of technologies for creating interactive Web applications. With Ajax, web pages exchange small packets of data with the server, instead of reloading an entire page. This reduces the amount of time that a user needs to wait when requesting data. It also increases the interactive capabilities and enhances the usability.

Using Ajax, developers can create fast Web pages using Javascript and asynchronous server requests. The requests can originate from user actions, timer events, or other predefined triggers.

Ajax components, also known as Ajax controls, are GUI based controls that use the Ajax technique—they send a request to the server when a trigger occurs.

For example, a popular Ajax control is a **Reorder List** control that lets you drag components to a desired position in a list. VuGen's support for Ajax implementation is based on Microsoft's ASP.NET Ajax Control Toolkit formerly known as Atlas.

For an overview on the Click and Script protocols, see "[Click & Script Protocols - Overview](#)" on [page 602](#).

## Ajax (Click & Script) Supported Frameworks

The supported frameworks for Ajax Click & Script functions are:

- Atlas 1.0.10920.0/ASP.NET Ajax—All controls
- Scriptaculous 1.8—Autocomplete, Reorder List, and Slider

VuGen supports the following frameworks at the engine level. This implies that VuGen will create standard Click & Script steps, but not Ajax specific functions:

- Prototype 1.6
- Google Web Toolkit (GWT) 1.4

## Ajax (Click & Script) Example Script

VuGen uses the control handler layer to create the effect of an operation on a GUI control. During recording, when encountering one of the supported Ajax controls, VuGen generates a function with an **ajax\_xxx** prefix.

In the following example, a user selected item number 1 (index=1) in an Accordion control. VuGen generated an **ajax\_accordion** function.

```
web_browser("Accordion.aspx",
            DESCRIPTION,
            ACTION,
            "Navigate=http://labm1app08/AJAX/Accordion/.aspx",
            LAST);
lr_think_time(5);

ajax_accordion("Accordion",
               DESCRIPTION,
               "Framework=atlas",
               "ID=ctl00_SampleContent_MyAccordion",
               ACTION,
               "UserAction>SelectIndex",
               "Index=1",
               LAST);
web_edit_field("free_text_2",
              "Snapshot=t18.inf",
```

```
DESCRIPTION,  
"Type=text",  
"Name=free_text",  
ACTION,  
"SetValue=FILE_PATH",  
LAST);
```

**Note:** When you record an Ajax session, VuGen generates standard Click & Script functions for objects that are not one of the supported Ajax controls. In the example above, the word FILE\_PATH was typed into an edit box.

## Ajax (Click & Script) Recording Tips

This section lists tips for recording click-and-script Vuser scripts.

**Note:** Some of the items below apply to specific click-and-script protocols only.

### Use the Mouse and not the Keyboard

It is preferable to click on an object with the mouse rather than using the keyboard. During recording, use only GUI objects that are within the browser's pane. Do not use any browser icons, controls, the Stop button, or menu items, such as **View > Refresh**. You may, however, use the Refresh, Home, Back and Forward buttons and the address bar.

### Do not Record Over an Existing Script

It is best to record into a newly created script—not an existing one.

### Avoid Context Menus

Avoid using context menus during recording. Context menus are right-click menus which pop up when clicking certain objects in a graphical user interface.

### Avoid Working in Another Browser While Recording

While recording, do not work in any browser window other than the browser windows opened by VuGen.

### Wait for Downloads

Wait for all downloads to complete before doing any action, such as clicking on a button or filling in a text field.

### Wait for Pages to Load

During recording, it is best to wait for the page to load completely before doing the next step. If you did not wait for all of the pages to load, record the script again.

### Navigate to the Start Page

If the last page in an action does not contain the links and buttons that were available at the start of the iteration, then the next iteration will fail. For example, if the first page has a text link **Book A**

**Flight**, make sure to navigate to the appropriate page at the end of your recording, so that the same link will be visible at the end of the business process.

## Use a Higher Event Configuration Level

Record the business process again using the **High** event configuration level. For more information on changing the event configuration level, see "[Click & Script Troubleshooting and Limitations](#)" on page 610.

## Disable Socket Level Recording

In certain cases, the capturing of the socket level messages disrupts the application. For most recordings, socket level data is not required. To prevent the recording of socket level data, disable the option in the recording options. For more information, see "[GUI Properties > Advanced Node](#)" on page 219.

## Enable the "Record rendering-related property values" Option

If the client-side scripts of the application use a lot of styling activities, enable the **Record rendering-related property values** option before recording the script. For example, enable this option to record additional DOM properties such as `offsetTop`. Note that enabling this option may decrease the recording speed. You can enable the option by selecting **Recording Options > GUI Properties > Advanced**. For more information, see "[GUI Properties > Advanced Node](#)" on page 219.

# Ajax (Click & Script) - Replay Tips

This section lists tips for replaying click-and-script Vuser scripts.

**Note:** Some of the items below apply to specific click-and-script protocols only.

## Do not Reorder Statements in a Recorded Script

Do not change the order of the statements within a recorded script. Also, copying segments of code from one Action to another is not recommended.

## Convert non-ASCII Characters

If your links contain non-ASCII characters, you should instruct VuGen to convert the data to or from the UTF-8 format.

## Enable UTF-8 Conversion

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the Advanced Options dialog box.
3. Locate the **Convert from/to UTF-8** option and set it to **Yes**.

Alternatively, view the list of options that is displayed when a link is not found. Enter the displayed text as-is, such as the hex escape sequences `\xA0` or any other non-standard format.

## Run the Same Sequence of Actions Twice

In some cases, you can perform a certain process only once—such as deleting a user from the database. Replay will fail after the first iteration because the action is no longer valid. Verify that your business process can be repeated more than once with the same data.

## Set Unique Image Properties

In the Step Navigator, double click on the previous image step to open its properties. If the **Id**, **Name**, and **Alt** properties are empty, provide further identification of the image, such as its file name in the **Src** property.

Alternatively, you can add an **Ordinal** argument to specify the occurrence number of the image on that page. The **Ordinal** argument uniquely identifies each image on the page where all other identification arguments are not unique. For more information, see the Function Reference ([Help > Function Reference](#)).

## Check the Step's Description

If you receive a **GUI Object is not found** error, check the Output pane for a list of the objects in the problematic step. In some cases, the object description changes slightly from run to run.

There are several solutions:

- If the new value is stable, open the script in the Editor and manually modify the value of the step's DESCRIPTION argument.
- If the description changes from run to run, you can use a regular expression in the DESCRIPTION argument. For more information, see the Function Reference ([Help > Function Reference](#)).
- Alternatively, replace the problematic object description property, such as Name, with the Ordinal property. For more information, see the Function Reference ([Help > Function Reference](#)).

### ThreadingModel

Replay of COM script in VuGen fails when the dll registration is missing the **ThreadingModel** string under the **InprocServer32** folder of the GUID.

## Ajax (Click & Script) Miscellaneous Tips

The following additional tips may help you in troubleshooting problems that you experience with click-and-script Vuser scripts.

**Note:** Some of the items below apply to specific click-and-script protocols only.

### Search for Warnings

Search for warnings or alerts in the Output pane.

### Verify the Response

Verify the response of the previous step is correct using **web\_reg\_find**. For more information, see

the Function Reference ([Help > Function Reference](#)).

## Use Alternate Navigation

For problematic steps or those using Java applets, use **Alternative Navigation** to replace the Web step with an HTTP level step. Note that the HTTP level steps may require manual correlations. To perform Alternative Navigation, select a step in the **Step Navigator**, or the text in Script View, and select **Replace with alternative navigation** from the right-click menu.

## Working with the Kerberos Protocol

If you are using the Kerberos Protocol for authentication, you must customize VuGen to properly convene authorization sessions. Advanced users can attempt to perform this customization themselves.

In order for the Kerberos Protocol to work properly, create a krb5.ini file and put it in an available folder. Save the full path name of krb5.ini into the KRB5\_CONFIG environment variable.

The krb5.ini file should contain detailed information about each domain (KDS and AS addresses) and trust chains.

For more information, contact HP software support.

# Click & Script Troubleshooting and Limitations

This section describes troubleshooting and limitations for click-and-script protocols.

**Note:** Some of the items below apply to specific click-and-script protocols only.

## Recording Issues and Limitations

### Browser support

- Only Internet Explorer is supported for Web (Click & Script). To record browser activity on Firefox, use the Web (HTTP/HTML) protocol.
- Not supported for Internet Explorer 10.
- For Click & Script protocols, VuGen may take an excessive amount of time to open the Recording Options dialog box.

### Language Support

- Recording an application in a specific language (e.g., French, Japanese) must be performed on a machine whose default locale (in **Settings > Control Panel > Regional Options**) is the same language
- Support of right-to-left languages is limited (e.g., bi-directional or reversed text may not be processed as expected). This is defined by the default operating system translation table.
- The locale of the load-generator machine, must be configured to be the same as that of the recording machine. It cannot be assumed that the Linux default character set is the same as in

Windows, even for US-English machines, and this has to be explicitly verified. For example, the default character set on Linux, is UTF-8.

### **Application behaves differently while being recorded**

If your application behaves differently during recording, than it does without recording, you should determine if the recording problem is unique to Web. The effect may be that a Web page will not load, part of the content may be missing, a popup window will not open, and so forth.

**Workaround:** Create a new Web (HTTP/HTML) script and repeat the recording.

In the event that the recording fails in Web (HTTP/HTML), we recommend that you disable socket level recording (see "[Click & Script Recording Tips](#)" on page 603).

The problem may be the result of an event listener. Use trial and error to disable event listeners in the **Web Event Configuration** Recording Options, and then re-record your session as a Web (HTTP/HTML) user.

### **Certain Click & Script steps do not generate properly**

After recording a script, if not all steps are correctly generated, the problem may be due to the **Windows Component > Internet Explorer Enhanced Security Configuration**.

Remove **Internet Explorer Enhanced Security Configuration** by selecting **Control Panel > Add or Remove Programs > Add or Remove Windows Components** and re-record your script.

### **Disable an Event Listener**

1. Click **Record > Recording Options** to open the Recording Options dialog box.
2. Select the **GUI Properties > Web Event Configuration** node.
3. Click **Custom Settings** and expand the **Web Objects** node. Select an object.
4. Select **Disabled** from the list in the **Record** column for the relevant Web object. If the recording still does not work, enable the listener you previously disabled, and try disabling another one. Repeat these steps until your recording succeeds.

### **Dynamic menu navigation was not recorded**

A dynamic menu is a menu that dynamically changes depending on where you select it. If the dynamic menu navigation was not recorded, record again using "high" event configuration mode. These settings can be found in the **Recording Options > GUI Properties > Web Event Configuration** node.

### **Certain user actions were not recorded**

Check if there is a Java applet running inside the browser. If not, record the script with the Web (HTTP/HTML) protocol.

## **Replay Issues**

### **GUI object not found**

Does the error occur at the beginning of the second iteration?

If the error occurs at the beginning of the second iteration's Action section, it is probably the result of a starting page that was present for the first iteration, but missing for the second one. If the last page in an action does not contain the links and buttons that were available at the start of the iteration, then the next iteration will fail. For example, if the first page has a text link **Book A Flight**, make sure to navigate to the appropriate page, so that the same link will be visible at the end of the business process.

Is it a text link containing non-ASCII characters?

If the problem occurs with non-ASCII characters, you should instruct VuGen to convert the data to a suitable character set.

## Enable Data Conversion on Windows Machines

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the Advanced Options dialog box.
3. Locate **Charset Conversions by HTTP** in the Web (Click & Script) > General options, and set it to **Yes**.

## Enable UTF-8 conversion for Linux Machines

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the **Advanced Options** dialog box.
3. Locate **Convert from/to UTF-8** in the General options and set it to **Yes**

Alternatively, view the list of alternatives that are displayed when a link is not found. Enter the displayed text as-is, such as hex escape sequences \xA0 or any other non-standard format.

Can you run the same sequence of actions twice in the application?

In some cases, you can only perform a certain process once, such as deleting a user from the database. Replay will fail after the first iteration, because the action is no longer valid. Verify that your business process can be repeated in the application more than once with the same data, without recording again.

Were the image properties 'Id', 'Name' and 'Alt' empty?

In the **Step Navigator**, double click on the previous image step to open its properties. If the **Id**, **Name**, and **Alt** properties are empty, provide further identification of the image, such as its file name in the **Src** property.

Alternatively, you add an **Ordinal** argument to specify the occurrence number of the image on that page. The **Ordinal** argument uniquely identifies each image on the page where all other identification arguments are not unique. For more information, see the Function Reference (**Help > Function Reference**).

Did the step's description change?

Check the Output pane for a list of the objects in the problematic step. In some cases, the object description changes slightly from run to run.

There are several solutions:

- If the new value is stable, open the Script View and manually modify the value of the step's DESCRIPTION argument(s).
- If the description changes from run to run, you can use a regular expression in the DESCRIPTION argument(s). For more information, see the Function Reference (**Help > Function Reference**).
- Alternatively, replace the problematic object description property, such as Name, with the Ordinal property For more information, see the Function Reference (**Help > Function Reference**).

Did the page load completely during recording?

During recording, it is best to wait for the page to load completely before doing the next step. If you did not wait for all of the pages to load, record the script again.

### **Replay failure**

If the replay fails at a particular step, check the step description. VuGen may have interpreted a single space as a double space. Make sure that there are no incorrect double spaces in the string.

### **Replay snapshots**

Replay snapshots may differ from the actual Web page.

## **Miscellaneous Issues**

### **Out of memory error in JavaScript**

Increase the JavaScript memory in the run-time settings.

### **Increase the JavaScript Memory Size**

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the Advanced Options dialog box.
3. Locate the **Memory Management JavaScript Runtime Memory Size (Kb)** and **Memory Management JavaScript Stack Memory Size (Kb)** options.
4. Increase the memory sizes to 512Kb or higher.

### **VuGen displays JavaScript errors**

If VuGen displays JavaScript errors in the Output pane, enable IE (Internet Explorer) script errors in order to verify that the Javascript itself does not contain errors.

## **Show Script Errors**

1. Open Internet Explorer.

2. Select **Tools > Internet Options** and click the **Advanced** tab.
3. Under **Browsing**, select the **Display a notification about every script error** check box.
4. Rerun the application in IE. If IE displays script errors, then there is a problem with the JavaScript application. If it is not possible to fix the application, you can safely ignore the corresponding replay errors.

#### **Problems following parameterization**

If you encounter problems only after you have parameterized values, verify that the values are valid for your application. Perform business process with the value of the parameter and verify that the application accepts it.

#### **Problems with applications that utilize styling actions**

If the client-side scripts of the application use a lot of styling activities, you should record the script again after enabling the **Record rendering-related property values** option. This enables the recording of additional DOM objects.

#### **Enable the "Record rendering-related property values" Option**

1. Select **Recording > Recording Options** and select the **GUI Properties > Advanced** node.
2. Select the **Record rendering-related property values** check box.

Re-record the Vuser script.

- ActiveX objects and Java applets are only supported on Windows platforms.
- Not supported for Macromedia Flash or VB Script.
- Click & Script protocols do not support pop-up windows.

## **TruClient Protocol**


### **What is TruClient?**

TruClient is a tool for recording complex web-based applications. The TruClient engine records your actions as you navigate through your business process. It creates a script in real-time, allowing you to see the steps as they are performed in a sidebar. Currently, you can select to record tests with either the Mozilla Firefox or Internet Explorer browser.

**Note:** This section documents features available in both the Mozilla  and Internet Explorer  browsers.

Features that are supported only by a particular browser are indicated by the browser's icon.

## The TruClient User Interface




The TruClient user interface is made up of the following sections:

- TruClient Sidebar.** The heart of the interface, containing all the tools you need to develop your TruClient scripts.
- TruClient Toolbox.** The toolbox contains all of the steps that you can add to a TruClient script. The toolbox opens and closes by clicking on the tab, and moves by dragging it up or down.
- Browser Navigation Bar.** Enter the URL of the application for which you are developing a script.
- Application Browser Window.** The window containing the browser where you develop and replay your script interactively.
- TruClient Sidebar Status Pane.** A pane that displays status details about the active action in the **TruClient Sidebar**.

You can watch a video demonstration about LR from the VuGen start page.

### The TruClient Workflow For LoadRunner

The TruClient protocol workflow is different from the workflow for other VuGen protocols. The following flowchart illustrates the basic TruClient workflow:




The following lists some of the main differences between the TruClient protocol and other VuGen protocols:

- The script is visible in VuGen's script view but it is read only. The script is created and modified in the **TruClient sidebar** in the browser (FF or IE).
- TruClient scripts are asynchronous. Steps do not have to wait for previous steps to complete. Each step defines an **End Event** which defines the point at which subsequent steps are allowed to start running.
- TruClient scripts are recorded on the user level, therefore there are no correlations, however ,the main challenge becomes object identification.
- TruClient scripts are replayed at the user level, therefore each Vuser requires a browser instance with loaded DOM and JavaScript. This makes resource footprint larger than the Web (transport based) protocol and also makes it dependent on the DOM and JavaScript of the application. For details see, "[How to Calculate the Number of Load Generators Required for TruClient Scripts](#)" [on page 513](#).
- All recorded events are saved in the script. Events deemed to be irrelevant are assigned to different script levels and are not replayed unless the level is manually changed by the user.
- TruClient transactions are defined by step events, not the steps themselves as in other protocols. For example, a step's End Event may allow the script to continue, while a transaction that ends on that step may continue until the step event that defines the transaction is reached.
- The Run-Logic in TruClient scripts is controlled differently. There is only one action.
- TruClient step arguments accept JavaScript code as values.

Most of the tasks involved in recording, replaying, and modifying scripts are done using the TruClient Sidebar for Internet Explorer or Mozilla Firefox .

## TruClient Step Structure

TruClient steps are comprised of a number of sections. The sections and elements within each section vary depending on the type of step.



User interface elements are described below:

### Step Structure

UI Element	Description
	<b>Drag Step.</b> Enables you to arrange the order of your script by dragging the step to a different location.
	<b>Expand Step.</b> Displays the individual components of the steps which include step, argument and object.
	<b>Script levels selector.</b> Allows you to view and modify the script level of the step. For more information, see " <a href="#">"TruClient Script Levels" on page 515</a> .
	<b>Replay.</b> Replays this step only.
	<b>Disable/Enable Step.</b> Steps that are disabled are not replayed. This feature allows you to temporarily remove steps from the script without deleting them.
	<b>Optional Step.</b> Marking a step as optional means that in the event that the step can not find its object, the script continues without returning an error.
	<b>Alternative Steps.</b> This icon indicates a step which can be redefined in alternative ways. To redefine the step, click the icon, select the desired step definition, and click Back. For more information, see " <a href="#">"TruClient Alternative Steps " on page 515</a> .

### Step Structure, continued

<b>Step</b>	<ul style="list-style-type: none"><li>• <b>Action.</b> The action that defines the step. The list of relevant actions is determined by the object roles.</li><li>• <b>Object Timeout.</b> If the object does not appear before this time in seconds, the step returns an error.</li><li>• <b>Step Timeout.</b> If the End Event is not reached by this time in seconds, the step returns an error. The way the script behaves when such an error occurs can be configured in the Run-Time settings dialog box.</li><li>• <b>Minimum Time.</b> The least time in seconds that the execution of the step will take. The value of this field can be either 0, "as recorded" or another manually set number.<p>The step execution will end immediately after the step's end event if minimum time is = 0.</p><p>A minimum time value greater than 0 forces TruClient to wait the additional time (if not elapsed already) from the step's end event before moving on to the next step.</p><p>TruClient records and stores the time that elapsed between recorded actions and allows you to set the minimum time to "as recorded".</p><ul style="list-style-type: none"><li>• <b>End Event.</b> TruClient defines when a End Event occurs during replay.</li></ul><p>An <b>End Event</b> can be one of the following:</p><ul style="list-style-type: none"><li>▪ <b>Automatic: Not Set Yet.</b> The automatic end event has not yet been determined.</li><li>▪ <b>Action Completed.</b> Step ends when its action is completed. An example of an action is a button click.</li><li>▪ <b>DOM content loaded.</b> Step ends when the page's Document Object Model (DOM) is ready. This means that the API for interacting with the content, style and structure of a page is ready to receive requests from your application client side code.</li><li>▪ <b>Step synchronous network completed.</b> Step ends when all HTTP requests have been completed excluding requests that are associated with open connections that are not relevant to the step. Usually, these requests are triggered by using XMLHttpRequest.</li><li>▪ <b>Document load.</b> Step ends when the process of loading a document is completed. This means that all scripts and stylesheets have finished loading and have been executed, and all images have been downloaded and displayed.</li></ul></li></ul>
-------------	--

### Step Structure, continued


	<ul style="list-style-type: none"><li>▪ <b>Step network completed.</b> Step ends when all HTTP requests have completed including requests initiated by XMLHttpRequest.</li><li>▪ <b>Dialog opened.</b> Step ends when a dialog box is opened.</li></ul> <p>For details, see "<a href="#">How to Synchronize TruClient Scripts Steps</a>" on page 508</p>
<b>Arguments</b>	Contains step arguments. These arguments differ for different step actions and roles. For a list of the step arguments, see " <a href="#">TruClient Step Arguments</a> " on page 579.
<b>Object</b>	<ul style="list-style-type: none"><li>• <b>Roles.</b> The functions that TruClient understands about an object. This information is read-only and is updated dynamically depending on how the object is used during recording. The list of available step actions is defined by these roles.</li><li>• <b>Name.</b> A logical name for the object. This does not affect replay and can be modified to enhance readability.</li><li>• <b>ID Method.</b> The method of identifying the object.<ul style="list-style-type: none"><li>▪ <b>Automatic.</b> TruClient's default object identification method. If this method does not successfully find the object during replay, click the Improve Object Identification button, reselect the correct object from the application, and replay the script again.</li><li>▪ <b>XPath.</b> Identifies the object based on its XPath expression that defines the object in the DOM tree. When you select this option, the next edit box in the display is labeled <b>XPath</b> and enables you to select an XPath to define the object. See below for details.</li><li>▪ <b>JavaScript.</b> JavaScript code that returns an object. When you select this option, the next edit box in the display is labeled JavaScript and enables you to define a JavaScript to define the object. See below for details.</li></ul></li><li>• <b>Related Objects.</b> Tool to enable TruClient to identify a target object in relation to an anchor object. For details, see "<a href="#">How to Resolve Object Identification Issues</a>" on page 519.</li></ul>
<b>Transactions</b>	Allows you to create, modify, and view transactions. For more information, see " <a href="#">How to Enhance TruClient Scripts</a> " on page 534.
<b>XPath/JavaScript</b>	

### Step Structure, continued

<b>XPath</b>	<p>TruClient generates several possible XPaths, depending on the object. Click the drop-down arrow next to the XPath edit box to select a suggested XPath for the object. You can manually modify the suggested XPath. To revert to one of the original expressions generated by TruClient, select one of the options from the drop-down again.</p> <p>You can also click the <b>Regenerate expression</b> button and select an object. TruClient generates a new set of suggestions based on the selected object.</p>
<b>JavaScript</b>	<p>If TruClient can generate a suggested XPath for the object, that XPath is entered as the argument in an <b>evalXPath</b> function in the JavaScript field. The <b>evalXPath</b> function returns an array of the objects defined by the XPath in the argument.</p> <p>You can modify the suggested XPath in the argument to return a different list of objects, or you can enter a different JavaScript. For example: <code>document.getElementById("SearchButton")</code> returns an element that has a DOM ID attribute of "SearchButton".</p> <p>TruClient also includes a <b>random</b> function that returns a random item from the array that is provided as its argument. For example: <code>random(document.getElementsByTagName("a"))</code></p> <p><b>Note:</b> The evalXPath and random functions are available as object identification methods only. They are not recognized in an Evaluate JavaScript code step.</p>

## Understanding Step Events

A TruClient step contains an action, and for application related steps, additional activity. The following diagram illustrates the sequence of events triggered as a result of step execution.



#### What is an End Event?

TruClient scripts are asynchronous. This means steps do not have to wait for previous steps to complete. Each step has an event flow and the **End Event** defines the point at which subsequent steps are allowed to start. During script replay, TruClient will determine each step's end event. For details see, "[How to Synchronize TruClient Scripts Steps](#)".

A step can be thought of as a container including an action and additional application activity. Each step execution differs and may go through a different event flow. The following examples illustrate how step execution can differ:

- **Example 1: Getting parameters using EvaluateJS step**

The step includes an Evaluate JS step with `TC.getParam("Name");`. In this step there is no application related activity. Therefore, the end event is automatically set to Action completed. The remaining events in the chain are not relevant.

- **Example 2: Click on a simple search box (no auto-suggest)**

This step interacts with the application but it does not trigger any network or DOM activity. Therefore, the end event is automatically set to **Action completed**. The remaining events in the chain are not relevant.

- **Example 3: Click on a search button**

This step interacts with the application and triggers both network and DOM activity. Therefore, the end event is automatically set to one of the events that follows **Action completed**. The event selected depends upon the specific application behavior.

#### When to manually change step end events

- **Case 1**

The next step is not ready to be executed because the preceding end event is incorrect. For details, see "[How to Synchronize TruClient Scripts Steps](#)".

- **Case 2**

You have created a transaction that surrounds several steps. You are interested in measuring a certain aspect of the transaction more accurately. For details, see "[Transaction Editor Dialog Box \(TruClient\)](#)" on page 550.


## How to Synchronize TruClient Scripts Steps

This task describes the process of synchronizing steps in TruClient Scripts.

**Note:** This task is part of a higher-level task. For details, see "[How to Develop TruClient Scripts](#)" on page 511

### 1. Interactively record the business process


TruClient scripts are asynchronous which means steps do not have to wait for previous steps to complete. Each step has an **End Event** which defines the point at which subsequent steps are allowed to start running. After the interactive recording, each **End Event** is set to **Automatic: Not Set Yet**.



For details on developing a script in TruClient, see Step 5 of ["How to Develop TruClient Scripts" on page 511](#)

## 2. Identifying the End Event

Before enhancing an TruClient script, replay the script to synchronize the steps. During the first script replay, TruClient will try to automatically identify the **End Event** for each step.



An **End Event** can be one of the following:

- **Automatic: Not Set Yet.** The automatic end event has not yet been determined.
- **Action Completed.** Step ends when its action is completed. An example of an action is a button click.
- **DOM content loaded.** Step ends when the page's Document Object Model (DOM) is ready. This means that the API for interacting with the content, style and structure of a page is ready to receive requests from your application client side code.
- **Step synchronous network completed.** Step ends when all HTTP requests have been completed excluding requests that are associated with open connections that are not relevant to the step. Usually, these requests are triggered by using XMLHttpRequest.
- **Document load.** Step ends when the process of loading a document is completed. This means that all scripts and stylesheets have finished loading and have been executed, and all images have been downloaded and displayed.
- **Step network completed.** Step ends when all HTTP requests have completed including requests initiated by XMLHttpRequest.
- **Dialog opened.** Step ends when a dialog box is opened.

If during the first replay, a step initiates the [Object Identification Assistant](#) to resolve object identification, the previous step's **End Event** will most likely be misidentified and TruClient will automatically reset it to **Automatic: Not Set Yet**.

### 3. Confirming the End Event

During the second script replay, TruClient confirm the Automatic End Event and will assigned any step's End Event that had been reset to **Automatic: Not Set Yet**.

If TruClient is unable to assign an automatic **End Event** during replay, usually due to a network timeout, a warning message will inform you that the **End Event** has been reset to **Automatic: Not Set Yet**. Replay the script to automatically assign the **End Event** or assign the **End Event** manually.

**Note:** You may need to replay the script several times until all steps have been accurately synchronized.

# Developing TruClient Scripts

## How to Develop TruClient Scripts

This task describes the basic steps involved in interactively developing an TruClient script.

### 1. Create a TruClient script from the VuGen toolbar.

For information about creating a VuGen script see, "How to Create or Open a Vuser Script" on [page 162](#).

### 2. Configure the General Browser Settings

The Browser Configuration settings allow you to configure settings that apply to all TruClient scripts. The settings are imported to new scripts as they are created. To edit these settings

click the **TruClient General Settings** button  from the Record toolbar in the VuGen main window and select the **Browser Settings** tab. For details, see "[TruClient General Settings Dialog Box](#)" on page 562.

### 3. Configure the Run-Time Settings

In VuGen configure the Run-Time settings before recording and performing a load test. To open the Run-Time settings dialog box, click **F4** or select the **Run-Time Settings** node from VuGen's **Solution Explorer**. For more information, see "[Run-Time Settings](#)" on page 317.

### 4. Start developing the script

Click  **Develop Script** to open an interactive recording session in the **TruClient Sidebar** for either the Mozilla Firefox browser or the TruClient browser for IE.

### 5. Record interactively

Navigate to the desired starting website and click  **Record** button . All of your actions will be recorded and displayed in the **TruClient Sidebar** on the left as you perform your business process. You can stop recording by selecting the **Stop** button . You can continue recording from any point in the script.

To record into different section of the script, right-click a step and select **Record > Record after** or **Record > Record before** to begin recording new steps into the desired location in the script. If you are recording into a group step, select **Record > Record into**. For more information on group steps, see "[TruClient Home Tab](#)" on page 553.

### 6. Replay the script

It is strongly recommended that you replay the script at least two times, correcting any errors that occur during the process. After two successful consecutive replays, you can move on to the next step. If you continue to experience errors, see "[How to Debug TruClient Scripts](#)" on

[page 517.](#)

During interactive replay, TruClient will animate each step progress according to its real running progress by filling the step bar. The step running progress can be for example: finding the test object, performing the action, or synchronizing the step on its end-event. For detail on synchronizing script steps, see "[How to Synchronize TruClient Scripts Steps](#)" on page 508.

In addition, script action details can be seen the **TruClient Sidebar Status Pane**.

## 7. Enhance the script

You can enhance your script in a number of ways such as inserting parameters, transaction, loops, and verification steps. For task details, see "[How to Enhance TruClient Scripts](#)" on page 534.

## 8. Stop developing

Click the Save button  to save the script. Close the browser window. Restore the VuGen window.

## 9. Replay the script in Load Mode

Before you run the script in a Controller scenario, run the script in VuGen's load mode. From the VuGen main window, click the **Replay** button  to replay the script in Load Mode . Progress can be monitored in the Replay log. The browser does not open, and snapshots are not displayed.

For details on Load Generation, see "[How to Calculate the Number of Load Generators Required for TruClient Scripts](#)" on the next page.

## 10. General Tips Regarding Successful Interactive Replay

Do not resize the browser between record and replay and during replay. This can cause objects to move and interfere with TruClient's ability to locate them.

Do not switch between applications during interactive replay. Keep the browser in focus.

**Note:** This is especially important when the Related Objects feature is used, as resizing may change the relative position of the objects.

**Note:**  Any customizations (such as bookmarks) that you make within this instance of Firefox will not be saved globally. This is because VuGen opens each script in a unique Firefox profile. If you want to use Firefox for any use other than creating this script (such as browsing the internet), we recommend that you open an additional Firefox window.

## How to Calculate the Number of Load Generators Required for TruClient Scripts

This task describes how to calculate the number of load generators required to run multiple TruClient Vusers in the Controller.

**Note:** This task is part of a higher-level task. For details, see "[How to Develop TruClient Scripts](#)" on page 511.

TruClient technology provides you with the ability to quickly and easily record complex business processes. However, because TruClient records at the user level and requires a browser for replay, the more complex an application's client logic is, the more CPU and memory is required to run a Vuser.

**Note:** The TruClient footprint can be significantly larger than the footprints of other Vuser protocols. This larger footprint will require more CPU and memory capacity than would be required to run a similar business process recorded in another protocol.

Use the following method to determine the required number of load generators:

1. Record a script using TruClient. For details, see step 5 of "[How to Develop TruClient Scripts](#)" on page 511.
2. Replay a single Vuser in Controller and check the average CPU and the peak memory consumption of the mdrv.exe process by adding a counter for **% Processor Time** and **Private Bytes**. For details on working with Windows Resource Monitors, see "[Add Windows Resources Measurements Dialog Box](#)" on page 1277.
3. Based on your load generator hardware and the CPU and memory consumption of a single Vuser, calculate the number of Vusers per machine.

For example:

Let us assume that each of our load generators has 8 core processors and 8GB of memory.

Let us also assume that a single Vuser consumes 80MB of peak memory and 10% CPU on average for the specific business process.

From a CPU perspective, if we limit the CPU consumption up to 70% utilization, we can have 7 Vusers per core processor (70% /10%). If our load generator has a total of 8 cores processors,  $8 * 7$  Vusers per processor equals 56 Vusers per load generator.

From a memory perspective, the load generator machine has 8GB memory of which 7GB is available for the Vusers so approximately 87 Vusers per load generator machine (7GB / 80MB).

Therefore, to meet both the CPU and memory capacity limits, we use the lower number of Vusers and we calculate that for this business process, we can run approximately 56 Vusers per load generator.

# TruClient - Debugging a TruClient Script

## ***TruClient Alternative Steps***

Alternative steps allow you to substitute an existing step with another step that performs the same action. This may be useful for debugging a script. For example, suppose your step selected an item from a menu, specified by the menu item number. TruClient lets you provide an alternate step that selects a menu item based on its name.

Steps that have alternative options are labeled with an alternative step symbol . Click it to view the alternative options for that step. Click the desired alternative and select **Back**.

Below is a snapshot of a step in which the second item in a listbox named "Desktop" was selected. The alternative steps feature gives you the option of defining the step based on clicking the link "Desktop", selecting the object "Desktop" from the listbox, or selecting the second item in the listbox.



## ***TruClient Script Levels***

As part of the process of recording a business process, some steps that are performed by the user while recording are not required during replay. TruClient removes steps it deems to be unnecessary and places them in different script levels. For example, a click step that occurs in an area of the application that has no effect is placed in level 2. TruClient assumes that this step is not significant and will not help the user to emulate a business process on the application. The default view displays level 1 steps only. To also review steps from levels 2 and 3, use the slide bar in the Home tab. During the replay phase, only steps that are visible are run.


In certain cases, you may want to override TruClient's decisions and manually change the level of a given step. This can happen in cases such as mouseover steps that are needed during replay. TruClient generally views mouse over steps as unnecessary for replay and assigns them to level 3. For more information, see ["How to Debug TruClient Scripts" on page 517](#).

**Note:** Automatic leveling during replay


The level of a step is normally set during recording according to the importance of the events in the business process. It can happen that an important step will look unimportant and will be placed in a lower script level. This may cause the replay to fail, generating an "object not found"

error. During replay, TruClient will check if there are steps in a lower level that can affect the outcome of the current step. If found, the meaningful step will be moved to higher script level.

The following screen shot displays a small script. Note that the step numbers skip from 1 to 3. Step 2 is hidden in a different level.



After changing the display settings by using the slide bar, all steps are now displayed and will run if replayed in interactive mode.



## TruClient Snapshots

Vuser scripts based on the TruClient protocol utilize VuGen's Snapshot pane.

- For an introduction to the Snapshot pane, see "[Snapshot Pane - Overview](#)" on page [85](#).
- For details on how to work with the Snapshot pane, see "[How to Work with Snapshots](#)" on page [88](#).
- For details on the Snapshot pane UI, see "[Snapshot Pane](#)" on page [126](#).

TruClient generates snapshots during recording according to the snapshot generation settings. These snapshots can be viewed by hovering the mouse over each step's icon. The snapshots are taken before the step's action is implemented and they are saved as .png files. Click each snapshot to display it in a new browser tab. Make sure that the correct tab is active before replay. Recording snapshots are stored in the snapshot folder.

You can configure snapshot generation during recording and replay by clicking the **General Settings** button  and selecting the **Interactive Options** tab. For details, see "[TruClient General Settings Dialog Box](#)" on page [562](#).

Snapshots can be viewed in snapshot viewer in VuGen. For details, see "[How to Work with Snapshots](#)" on page [88](#). You can also view snapshots in the TruClient snapshot viewer. For details, see "[TruClient Home Tab](#)" on page [553](#).

TruClient can also generate snapshots during load mode according to your specifications in the run-time settings. For details, see "[General > Replay Node](#)" on page [343](#).

Replay snapshots are stored in the results folder and are organized according to the type of replay (interactive or load), the script section, and the iteration.

## How to Debug TruClient Scripts

This task describes different options to debug an TruClient Script.

### View Replay Errors in the TruClient sidebar

If any steps failed during replay, they are marked with an error  icon. Hover the mouse over these icons to view descriptions of the errors.

### Run The Script Step by Step

You can run your script step by step to view the replay more slowly and in a controlled manner. To run the script step by step, select the down arrow from the replay button in the browser and select **Replay step by step**. Repeat this procedure after each step to continue the step by step replay.

### View the Replay Logs

In the VuGen Output Pane, you can view details of your script's replay. Select **Output Pane > Replay** or the **Output Pane > Browser Replay** logs . For details, see the "[Output Pane](#)" on page [124](#).

## Insert Toggle Breakpoints

Breakpoints instruct the script to stop running during a replay when in interactive mode. They can be used to help debug your script. To insert a toggle breakpoint, select the desired step and click the Breakpoints  button.

## Debug Scripts Using Snapshots

You can use the snapshots generated during replay to debug scripts by viewing the snapshots of the failed step(s).

1. Select the  button on the **TruClient Sidebar** and select the **Interactive Options** tab. Set the **Replay Snapshots Generation** to **On Error**.
2. Replay the script from the **TruClient Sidebar**.
3. Look in the **Output Pane > Replay** or the **Output Pane > Browser Replay** logs for errors. Note the step numbers of the steps that had errors.
4. To view the snapshots from the **TruClient Sidebar**, select a step with an error, and select the  button.

or

To view the snapshots from VuGen, select **View > Snapshot Pane**.

You now have a group of snapshots in which errors occurred in the script.

## Modify and view script levels

Sometimes, steps that were recorded and are necessary for replay are placed in levels 2 and 3. In this case, you need to manually modify the level of those steps to level 1.

- To modify a the script's replay level, drag the slider in the toolbar to the desired level. Dragging the slider to level 3 displays and replays the steps on levels 1, 2, and 3.
- To move a step to a different level, open the step and click on the step section. Move the slider to the desired level. If the step is part of a group step, both the group step and the individual step must be modified.

For more information, see "[TruClient Script Levels](#)" on page 515.

## Insert Wait steps

Sometimes a script will fail to replay because an object in a step is not available when the previous step has finished. You can resolve this by inserting **Wait Steps** into your script which pause the script replay before continuing to the next step. There are two different types of **Wait Steps**:

- The **Wait** step pauses the script for a specified amount of time before continuing to the next step.

- The **Wait for Object** step pauses the script until a specified object is loaded before continuing to the next step.

**Wait Steps** begin after the **End Event** of the previous step. This means that the previous step may continue to run after the **Wait Step** has been reached.

To insert a **Wait Step**, select **Toolbox > Functions** and drag the **Wait** or **Wait for Object** icon to the desired location in your script. If you add a **Wait** step, configure the interval in the argument section of the step. If you add a **Wait for Object** step, select the **Click to choose an object** button to select the target object in the application.

**Note:** **Wait Steps** differ from **Think Time** steps in other protocols. **Think time** controls the time that a VuGen waits between actions. **Wait Steps** pause a script replay until either a specified time elapses or an specified object is loaded.

## **Additional Script Debugging Tips**

### **Alert Function**

Since all the TruClient arguments support JavaScript, you use the **Alert** function to display information during script development. You can also reference any DOM element using regular functions, such as `location`.

### **Firebug for IE or Dom Inspector for FF**

To further improve debugging capabilities, you can install plug-ins such as DOM Inspector and Firebug that can provide additional information on the application object properties.

For more information on Firebug Lite, see "[TruClient Browser for IE](#)" on page 561

### **Resolving Step Timeouts**

Steps may timeout due to several reasons:

- Application is responding slowly, possibly under load. This is actually an important test result.
- Step Timeout is incorrect and should be modified via the Step section of the step properties.
- The end event of the step is incorrect and the step is waiting for an event that does not occur. The end event should be changed via the Step section of the step properties.

## **How to Resolve Object Identification Issues**

Object identification presents one of the biggest challenges with recording and replaying Web 2.0 applications because objects which have been recorded can move or change content. When recorded objects change dynamically during replay, TruClient can lose the ability to automatically locate the object.

TruClient includes sophisticated mechanisms to overcome this challenge including the Highlight, Improve Object Identification, Replace Object and Related Object, and Object Identification Assistant options. The following steps describe the ways to use these mechanisms.

**Note:**  When identifying objects for applications that have been recorded in multiple windows, make sure that the correct window is selected in the **TruClient Sidebar > Window Tab > Replay Window**.

Highlight, Improve Identification, Replace, and Related Objects all require the user to select an object in the application. There are cases in which various actions are required in the application to make the object visible such as mouse over and mouse click. In these cases use the CTRL+ALT+F4 to suspend the TruClient object selection mode until you've brought the object into view and press CTRL+ALT+F4 again to select the object.

**Tip:** After you perform any of the changes, replay the single failed step in question and only afterwards replay the whole script again. This will help verify whether the change has solved the issue you encountered.


The following steps describe the ways to resolve object identification issues.

## Highlighting an object

Regardless of which method of object identification is used, you can use the highlight  button, located in the Object section of the step, to check if an object is visible in the application at any time. If the object is not found this may be an issue of pacing and timing. If the object cannot be found, an error message is displayed.

## Improve Object Identification

If the Highlight option fails, use the Improve Object Identification.



This option is located in the Object section of the step, next to the ID Method drop-down. This will let TruClient relearn the properties of the object and compare them to the properties learned during recording. Based on the differences, the necessary adjustments can be made. Depending on how dynamic the application is, you may need to use the Improve Object Identification function more than once.

Once you have done this, try replaying the step again to verify that the problem has been solved.

## Alternative Steps

Alternative steps allow you to view instances in which there are multiple ways to perform the same

action in a step. If Improve Object Identification fails, try using one of the alternative steps.

For example, you may be clicking on an option in a drop-down list in which the text changes based on some value.

If you try to click based on the text, the step may fail.

If you use an alternative step that selects the item in the list based on the ordinal value of the option within the list, the click will succeed regardless of the text.

**Note:** Before selecting one of the alternatives, try highlighting the object used by the alternative step and replaying it. This way you can make sure the alternative step is replaying the necessary action.

## Modify the Object Identification Method

You can modify the way TruClient identifies the object by modifying the object identification method in the Object section of the step properties. The following options are available:

- **Automatic.** TruClient's default object identification method. The Automatic method allows TruClient to use its internal advanced algorithms to locate the object. If this method does not successfully find the object during replay, click the Improve Object Identification button and replay the script again.
- **XPath.** If Automatic identification fails, even after using Improve Identification or Related Objects (described below), try using the XPath identification method. This method identifies the object based on an XPath expression that defines the object in the DOM tree. Click the drop-down arrow next to the **XPath** edit box to select a suggested XPath for the object. You can manually modify the suggested path. To revert to one of the original expressions generated by TruClient, select one of the options from the drop-down again.

For example, if you need to select the first search result, regardless of the term being searched for, using XPath identification may help.

- **JavaScript.** JavaScript code that returns an object. For example: `document.getElementById("SearchButton")` returns an element that has a DOM ID attribute of "SearchButton".

Using the JavaScript identification method you can write JavaScript code that references the returned document and can use CSS selectors and other standard functions.

For example, the page returned by the server contains multiple links with the same "title" attribute (search results) and we want the script to randomly click on one of the available links.

Object identification for this case, using the JavaScript identification method, may look something like this:

```
var my_results = document.querySelectorAll('a[title="SearchResult"]');
random(my_results);
```

## Modify the script timing

Sometimes objects may not be found because of timing and synchronization issues. For example,

the script may be looking for an object that was in the application, but the script replayed too quickly and already progressed to another page. If you suspect that the object is not being found because of a timing or synchronization issue, you can insert Wait steps. For more information, see "[How to Debug TruClient Scripts](#)" on page 517.

## Relating objects to other objects

If the **Improve Object Identification** function does not solve the issue and neither do any of the alternative steps, try using the **Related Objects** option.

If an object becomes difficult to identify on its own, you can label the object based on a different, more stable object. For example, you can select an object which is not dynamic and "relate it" to the target object. Relations are defined visually, relating objects according to their distance in pixels from other objects. Relations are defined per ID method, per object. If more than one relation is defined for an ID method of a given object, both relations must locate the same object for the step to pass. TruClient then uses this object to help locate the target object. To use this function, expand the step, select **Object > Related Objects**, and click the add button . Follow the directions to create a relation. Verify that it has worked by highlighting both the object and its related object.

### Tips:

- Use this feature only if other identification methods have failed as it may be more resource intensive.
- Use the minimum search area to improve performance.
- Related Objects are sensitive to window sizing. Resizing may alter object positions and relationships. This should be taken into account.
- Each identification method (Automatic, XPath, and JavaScript) has its own set of related objects. These related objects are not shared between identification methods.
- If several relations exist they all need to be found in order for the identification to succeed.

## Replacing an object

If you selected the wrong object during recording, or an object has permanently changed, you can replace it with a different object without replacing the step. This effectively resets the step, deleting changes made to the original step such as relations. Expand the step, select **Object**, and click the

 **Replace** button  . Select the new object and replay the script.

Replace Object will tell TruClient that the object currently referenced in the step is incorrect. TruClient will remove any current knowledge of the object and learn the object you select.


Therefore, you should only use the Replace Object option if the object you used during recording was the wrong one.

## Object Identification Assistant

Object identification can fail during replay for several reasons. For each reason, TruClient will launch the object identification assistant to try to resolve failed identification.

## Cannot confirm object

TruClient suspects a specific object to be the desired object but it cannot be positively identified. The suspected object is highlighted on the screen, and the following assistant dialog box appears:




Options:

- **Yes.** The suspected (and highlighted) object is the correct object.
- **Locate.** The suspected object is not the right object. You will need to identify the correct object in the application.
- **Cancel.** Stop the replay.

## Multiple objects found

TruClient found several objects that match the identification of the desired object. All suspected objects will be highlighted on the screen, and the following assistant dialog box will appear:




Options:

- The correct object is one of the marked objects. Click the object in the application to specify the correct one.
- **Locate.** The suspected object is not one of the highlighted objects. You will then need to highlight the correct object in the application.
- **Cancel.** Stop the replay.

### Object not found

TruClient could not find the desired object. The following assistant dialog box will appear:



Options:


- **Locate.** Locate the object. You will need to highlight the correct object in the application.
- **Cancel.** Stop the replay.

### Wrong level on step

TruClient found that a step in a higher level is needed for the identification of the object of current step. This is common for mouse over steps that are usually recorded in level 3 but might be needed for click steps that are recorded in level 1.

When TruClient recognizes this dependency during **recording**, the mouse over will move automatically to level 1.

When TruClient recognizes this dependency during **replay**, the following assistant will appear:



Options:

- **Yes.** Move the needed step to level 1.
- **Cancel.** Stop the replay.

## Troubleshooting Object Identification Issues

### How Related Objects Can Help the XPath and JavaScript Identification Methods

The XPath and JavaScript identification methods may return multiple elements depending on the expression used.

For example, if the XPath value is //button, and the web page in question includes multiple button elements, multiple objects will be returned.

To return a single object you can add a Related Object that will narrow down the identification.

## Interactive Replay Fails with Object Not Found Error

If replay stops with an error that says the object was not found try the following:

- Select the failed step and press Highlight. If the correct object is not highlighted use Improve Identification to improve object identification.
- If the object is highlighted it may be that step was reached before the object appeared. Add a Wait or Wait for Object step before the problematic step.

Sometimes you may need to choose an Alternative Step that is provided in order to solve the issue. For example, you may be clicking on an option in a drop-down list in which the text changes based on some value. If you try to click based on the text, the step may fail. If you use an alternative step that selects the item in the list based on the ordinal value of this option within the list, the click will succeed regardless of the text.

## Interactive Replay Fails Due to Object Not Found Although Highlight Locates the Object

If the replay fails even though the Highlight option finds the correct object, this may be a case of pacing.

The object takes a little longer to load and the step is executed faster. Therefore, during execution the step cannot locate the object although, during debugging, the Highlight option on the failed step finds the object.

In this case it is recommended to "slow down" the script so there is enough time for the object to load. Use one of the following options to do this:

- Change the Object Timeout of the failing step. This is available via the Step section on the step's properties.
- Add a Wait or Wait for Object step before the failed step.

## Replay Fails to Select an Item from a List

One of the common reasons for this is that the names of the items in the list are dynamic.

For example, the list may include a list of cities based on the text entered so far (auto-complete).

Based on the text types the list constantly changes.

There are two ways to solve this issue:

- Use an alternative step that selects an item from the list using the ordinal identifier instead of the text of the actual item.
- If the text is only partially dynamic you can use a regular expression to locate the required item based on partial text matching.

## Troubleshooting TruClient Scripts

### How to Check for Specific Text Including Branching

One option is to add a Verify step from the Functions section of the Toolbox. In this step you can select various validation settings such as the object, the text to look for, and so on.

When you want to perform certain actions based on whether a validation succeeded or failed you add a Catch Error step from the Flow Control section of the Toolbox.

This way you can make sure the step continues even if the validation failed and within the Catch Error group you can define the set of steps that should be executed if the validation fails.

You can also take a more programmatic approach to validations. Using JavaScript you can access the DOM and validate any property you wish to verify. You can then add a conditional Break or Exit step (available via the Flow Control section of the Toolbox) based on this verification.

You can also check for the required text directly from the IF statement. The 'condition' argument of the IF statement is simply JavaScript code. You can use JavaScript code that accesses the window global object of the application under test. This can be done by referring to window.

Then you can manually verify if the text exists within the current page. For example, assuming a single frame application, you can write something like:

```
window.document.body.textContent.indexOf("Off") == -1
```

Where "Off" is the text you're looking for and -1 indicates that the text was not found.

The code in question is application specific.

You can optimize the code if you have further knowledge of the application (by getting the specific element).

### How to Check for Specific Text that is Case Insensitive

By default, the Verify step is case sensitive. For example, looking for 'Test' will fail if 'test' is found.

If you would like the Verify step to be case insensitive do the following:

- In the Verify step set the Condition argument to "Regular Expression"
- To check if the string 'test' is contained in the text regardless to case you can use:

```
RegExp("test", "i")
```

### How to Select a Random Option from a List

Set the Ordinal argument to 0. TruClient will automatically select a random option from the list.

For example, let's assume you have an auto-complete list that shows a list of cities based on the typed text. You've currently selected the second option and the step is: Select option #2 from City autocomplete.

All you need to do is open the Arguments section of the step properties and change the Ordinal argument to 0. The step will now be: Select a random option from City autocomplete.

This option is very important when the typed text is a parameter and therefore you have no easy way of knowing in advance what values exist in the list and how many there are.

## How to Use External Functions in the Script

Add your JavaScript and C functions to the JS-Function.js and C-functions.c files that are part of the script and appear in the left navigation pane in VuGen.

JavaScript functions can be called directly from the TruClient script, as all arguments and parameters support JavaScript. You can also add an Evaluate JavaScript or LR.evalC step from the Toolbox for this purpose.

To call C functions add an Evaluate C step from the Toolbox.

## Some of the Events and Actions do not Appear in the Recorded Script

Try solving this in one of the following ways:

- TruClient records all the events in the application. The event you're looking for may be in a different script level from the one being displayed.
  - You can tell that additional steps exist in other script levels if the steps in the viewed level are not numbered consecutively.
  - The current script level is set using the slider in the toolbar:

Try looking for the missing event or step in the other levels by changing the slider value.

- Once you have found the required event, you can change its level and make it part of level 1.
- Change the script level back to level 1 and try to replay it again.
- You can manually add a step to the script.
  - From the toolbox select the Generic Object Action and customize the step to perform the required action.

## Dragging of a Slider or a Map does not Replay Correctly

If drag does not work (e.g. set option of slider, drag of map) and the result does not bring the control to the appropriate place try the following:

- Try using one of the Alternative Steps.
- Set the values manually until they meet your needs (e.g. the precise number of pixels you would like to drag in each of the relevant directions).
- Try using the "Drag to" capability (by changing the Action of the Drag step in the Step section of the step properties). This way you can drag your object to a relative position from another object.

## Polling for an Object

Create a loop that includes the following steps:

- A step that performs an action on an object.
- A Catch Error section that includes a Continue step.
- A Break step.

The Catch Error section will make the loop continue until the object is found and the step succeeds.

## **How do I Create a WHILE Loop**

A "For" loop has 3 arguments: Init, Condition, and Increment.

A "While" is basically a "For" loop with only the Condition argument.

To create a while loop add a "For" loop (using the context menu or the toolbox), delete the Init and Increment arguments and specify the Condition.




## TruClient - Enhancing a TruClient Script

### ***TruClient Event Handlers***

Event handlers are designed to manage events that can occur at any time during the run of the script. The event trigger is set to an object appearing in the application with or without an additional specified property. The handler (action) of the event is a function selected from the script's function libraries.

During the replay of the script, when moving from one step to the next, TruClient checks to see if a defined event occurs and if it does, it runs the function associated with the event.

The flowchart below illustrates the Event Handler workflow using the business process example of buying and selling of stocks.



For details, see :

- "How To Use The Events Handler" on page 536
- "TruClient Events Handler Editor Dialog Box" on page 544

## ***TruClient Functions and Function Libraries***

A TruClient function is a group of steps, such as a login, that you define as a function. Functions are stored in libraries that can be reused multiple times in a script. Each library can contain multiple functions.

Each library can be either local or global. A local library can be accessed by the script that created it. A global library can be accessed by all TruClient scripts. Additionally, a global library can be saved on the network and shared between many users.

For details on creating and using function and function libraries, see "[How To Create and Use Function and Libraries](#)" on page 542.

## ***Working With JavaScript in TruClient Scripts***

The following section contains tips for recording TruClient scripts.

### ***JavaScript Support***

The arguments listed in the Arguments section of each step are all JavaScript based and can accept JavaScript expressions which will be evaluated during script replay. It is important to remember that to provide a string value, quotation marks are required. For example: City will be interpreted as a variable whereas "City" or 'City' will be evaluated as a string.

All other sections such as Step, Object, Transactions, are not JavaScript based, are not evaluated as JavaScript, and do not support JavaScript expressions. The only exception is object identification using JavaScript.

However, object identification variables and step variables do not share the same context. Variables that are defined in one context are not recognized in the other. To use a variable in object identification that is defined in a step, add the prefix **ArgsContext** before the variable name. For example, if the variable **firstname** is defined as a value for an argument of a step, it cannot be used in object identification. To use the **firstname** variable in object identification, refer to the variable as **ArgsContext.firstname**.

### ***How Can I Learn More about JavaScript***

JavaScript is the scripting language of the Web. JavaScript is used in millions of Web pages to add functionality, validate forms, detect browsers, and much more. The Internet is full of resources for learning JavaScript and can be located using search engines.

An example of some tutorials and references:

<http://www.javascriptkit.com/jsref/>  
<http://www.w3schools.com>  
<http://www.learn-javascript-tutorial.com/>

## Using Regular Expressions

To use regular expressions, there are two options:

- Use the '/' notation: Replace the quotation marks of a string with a slash.

For example:

/LoadRunner/ is a regular expression that will match any string that contains the word "LoadRunner" in it.

- If you need to dynamically create a regular expression (e.g. using a parameter), you can use the regular expression constructor and specify the string. For example, the equivalent of the above example is RegExp("LoadRunner").

The full list of supported regular expressions can be found here:

[https://developer.mozilla.org/en/JavaScript/Reference/Global\\_Objects/RegExp](https://developer.mozilla.org/en/JavaScript/Reference/Global_Objects/RegExp)

## How to Enhance TruClient Scripts

There are a number of optional enhancements that can be added to scripts beyond the basic workflow. This task describes the enhancements and how to use them.

### Modify Steps

Modify step arguments and objects by selecting the desired step and expanding the options. This expands the step and allows you to modify the objects and properties. For a detailed list of the step structure, see ["TruClient Toolbox" on page 558](#).

- Insert Flow Control Steps

Loops repeat selected portions of the script until certain criteria is met or for a specified number of times. To insert a loop, select **Toolbox > Flow Control > For loop**. For more information, see ["How to Insert and Modify Loops" on page 538](#).

- Insert If blocks or If-else blocks and exit steps

To conditionalize a portion of the script, you can insert If or If-else blocks. To insert an If block, select **Toolbox > Flow Control > If block**. To add an else condition, click the **Add else** link next to the If step title. For more details, see ["TruClient Step Arguments" on page 579](#).

Exit steps cause a script to exit the iteration or the entire script. These can be used with If statements to exit a script or iteration when a specified condition occurs. To insert an exit step, select **Toolbox > Flow Control > Exit**.

## Insert comments

You can insert comments into your script by selecting **Toolbox > Misc** and dragging the **Comment** icon to the desired location.

## Insert Transactions

You can add transactions by using the Transaction Editor. To open the Transaction Editor click the Transaction Editor  button from the Home Tab or click Ctrl + Alt + F7. TruClient transactions function differently from other protocols because of the asynchronous nature of TruClient steps. Transactions are defined based on start and end steps and step events. Due to this definition, a transaction's end can be triggered before the true end of a step.

If **Run-time settings > Replay > enable profiling** is selected, client side breakdown information is displayed in the private browser for each transaction after the script is successfully replayed. For details, see "[TruClient Client Side Breakdown Data](#)" on page 547.

## Create Parameters

Parameters for TruClient scripts can be created in the standard method as for all protocols.

Parameters can be referenced and created within step arguments or Eval JavaScript steps.

To parametrize a value:

1. Select a field in the step Arguments area.
2. Highlight either the entire string or part of the string.
3. Right-click and select **Replace with a Parameter**.
4. In the Enter Parameter Name dialog box, enter the name of a new or existing parameter.

If the parameter does not exist in the **Parameter List**, it is created and the default parameter type is set to **File**. You can go to the **Parameter List** to add or delete values for the specified parameter. By default, the original value is included in the list of values for the new parameter. For details, see "[How to Work with Existing Parameters](#)" on page 416.

The following is an example of how to use a parameter in your script. This string can be used as the Argument in an Evaluate JavaScript step:

During replay it returns the current value of the parameter **paramname**.

```
LR.getParam("paramname")
```

During replay it assigns the parameter **paramname** the value **value1**.

```
LR.setParam("paramname", "value1")
```

For example, let us assume we have an auto-complete list that has a different set of values based on the text that's typed.

Trying to select an option in the list based on the text of the option is bound to fail once the typed text is defined by a parameter. The options are changed every time the parameter value is updated.

In these cases the step that uses an ordinal value is more appropriate.

For more details on parameters, see the section on "[Parameters](#)" on page 408.

### **Insert Catch Error Steps**

Catch error steps are group steps that run their contents if the previous step contains an error. Additionally, the error is "caught" and is not returned. You can define catch error steps to catch any error, or a specific type of error. If there are two catch error steps in a row, they both apply to the same step. To insert a catch error step, select **Toolbox > Flow Control > Catch Error**.

### **Verify that an objects exist**

To verify that a string or object exists in the application, you can insert a verify step:

1. Select **Toolbox > Functions** and drag the **Verify** icon to the desired location.
2. Click the object in the verify step.
3. Select the object you want to verify.

### **Insert Generic Steps**

You can insert a blank step and manually configure it. To insert a generic step, select **Toolbox > Functions > Generic Object/Browser Action**, drag and drop the step to the desired location. Next, expand the step, and enter the desired step properties. Generic Object Actions perform an unspecified action on an object. Generic Browser Actions perform an unspecified action on the browser such as go back, reload and switch tabs.

## **How To Use The Events Handler**


This task describes how to create and use events with the Global Events Handler. For an illustration, see "[TruClient Event Handlers](#)" on page 531.

### **Prerequisites**

The Global Events Handler runs functions if a certain event occurs during the replay of the script. Before you create handlers, you must create the associated functions. For details, see "[How To Create and Use Function and Libraries](#)" on page 542.

### **Create an Event Handler**

1. Click the  button from the TruClient Toolbar. This will open the Event Handler Editor



2. Click the button from the Event Handler pane.



3. Define the properties of the handler.

You can specify if you want the handler to run at any time during the script or only between certain steps. For details on this and other properties, see "[TruClient Events Handler Editor Dialog Box](#)" on page 544.

### Define object associated with event

Select the object in the application with the button on which the event will occur.

For example, select the text box for the widget StockPrice if you wish to trigger the function SellStock, if the stock prices rises over \$99.99.

Once the object is selected you can select the button to verify that the correct object was selected. Additionally, you can select the button to replace the selected object with another one. For details, see "[How to Resolve Object Identification Issues](#)" on page 519.

## Define the event

You can select to run the handler if the object exists or if, object's properties meet specific conditions. For details, see "[TruClient Events Handler Editor Dialog Box](#)" on page 544.

## Assign handler to the event

Select the function library, the function and specify argument values. For details, see "[TruClient Events Handler Editor Dialog Box](#)" on page 544.

## Enable the handler

To enable the handler during script replay, select the check box next to the handler in the Event Handler Pane.



## How to Insert and Modify Loops

Loops repeat selected portions of the script until certain criteria is met or for a specified number of iterations. You can insert loops and loop modifiers from the **Flow control** section of the **Toolbox**.

### For Loops

**For loops** perform the steps surrounded by the loop until the end condition is met or the code reaches a break statement. Loops arguments use JavaScript syntax. To insert a for loop, select **Toolbox > Flow Control > Functions > For Loop**.

### Break statements

**Break** statements indicate that the current loop should end immediately. For example, if a break statement is encountered in the second of five iteration in a for loop, the loop will end immediately without completing the remaining iterations. To insert a break statement, select **Toolbox > Functions > Flow Control > Break**.

### Continue statements

**Continue** statements indicate that the current loop iteration should end immediately. The loop condition is then checked to see if the entire loop should end as well. For example, if a continue statement is encountered in the second of five iterations in a for loop, the second iteration will end immediately and the third iteration will begin. To insert a continue statement, select **Toolbox > Functions > Flow Control > Continue**.

## **How to Insert Custom JavaScript and C Code into TruClient Scripts**

This task describes how to insert code into an TruClient script. You can insert code into a pre-existing step as part of a step argument or insert steps that are completely comprised of external code (C or JavaScript).

### **1. Insert code into a pre-existing step**

You can insert JavaScript code into pre-existing steps in the arguments fields of most steps. This allows you to perform multiple customizations.

### **2. Insert steps composed entirely of code**

You can insert steps comprised entirely of code into your script. To do so, select **Toolbox > Miscellaneous** and drag the **Eval Javascript**, **Eval C**, or **Eval JS on Object** icon to the desired location. The **Eval JS on Object** step runs the JavaScript code after the specified Object has loaded. We recommend avoiding Eval C and using JavaScript instead wherever possible. You can refer to this object as the variable "object" in the JavaScript code within the step.

#### **Example:**

The following code creates a variable called amount that generates a random number between 1 and 5. You can then use this variable in the argument fields of other steps.

```
var amount=Math.floor(Math.random()*5)+1;
```

## **How to Use VTS in TruClient**

This task describes an example of how to use VTS in a TruClient script.

### **What is VTS?**

- HP LoadRunner Virtual Table Server - or VTS for short - is a web-based application that is built to work with LoadRunner Vuser scripts. VTS offers an alternative to standard LoadRunner parameterization.
- When you use standard LoadRunner parameterization, each Vuser is assigned parameter values from a dedicated set of values - parameter values are not shared between Vusers. In contrast, VTS enables you to assign parameter values from a single set of parameter values to multiple Vusers. This may enable you to more accurately emulate a real-user environment.
- VTS includes a table that contains parameter values that can be used by your Vuser scripts. The VTS table is composed of columns and rows. Each column represents a set of values that can be used by a specific parameter in your Vuser scripts. The cells within a column contain the actual values of the parameter.

## How to connect/disconnect to a VTS server

1. Select **Toolbox > Miscellaneous** and add a  Evaluate JavaScript step to your script.
2. To connect to a VTS, enter `TC.vtcConnect("server", port, "alias")` in the **Arguments > Code** section of the step.  
You can identify the server either by name or by ip address.  
  
Example: `TC.vtcConnect("myServer", 8888, "myVTS");`
3. To disconnect from a VTS, enter `TC.vtcDisconnect("alias")` in the **Arguments > Code** section of the step.

**Tips:**

- Before you replay the script, play the `TC.vtcConnect` step (from within the step) to verify the connection to the VTS server.
- Once you have established a connection to the VTS server, you can play other VTS API steps, modify them and replay again.
- Replying the entire script will automatically disconnect the VTS even if there is no disconnect step in your script.

### Examples of connecting and disconnecting to a server:

- Using a server name and alias

```
TC.vtcConnect("MyServer", 8888, "UsersTableVts");
```

```
TC.vtcDisconnect("UsersTableVts");
```

For details on the use of aliases, see ["How to Use VTS in TruClient" on the previous page](#).

- Using the server ip address and alias

```
TC.vtcConnect("192.168.1.133", 8888, "WorkersTableVts");
```

```
TC.vtcDisconnect("WorkersTableVts");
```

- Using the server name without an alias

```
TC.vtcConnect("MyServer", 8888);
```

```
TC.vtcDisconnect();
```

- Using the server ip address without an alias

```
TC.vtcConnect("192.168.1.133",8888);
TC.vtcDisconnect();
```

## Why do you need an alias for your VTS server?

If you are using more than one server, creating an alias for each server will simplify identifying which VTS your are referencing in your code.

### Examples:

In the connect statement below, "UserTableVts" is an alias for "MyServer".

```
TC.vtcConnect("MyServer",8888,"UserTableVts");
```

In the example below, we are connecting to two VTS servers and disconnecting, by alias, to the first one:

```
TC.vtcConnect("MyServer", 8888, "UserTableVts");
TC.vtcConnect("MyServer1",8888, "ScriptDataVts");
TC.vtcDisconnect("UserTableVts");
```

## How to use Eval JavaScript code step to pass VTS parameters to another step.

You can use the Eval JavaScript code step to pass VTS parameters to another step in your script. The example below shows you how to parametrize a URL.

1. Connect to a VTS server
  - a. Select **Toolbox > Miscellaneous** and add an  Evaluate JavaScript step to your script.
  - b. To connect to a VTS, enter `TC.vtcConnect("server",port,"alias")` in the **Arguments > Code** section of the step.
2. Create a step that contains a variable.
  - a. Select **Toolbox > Miscellaneous** and add an  Evaluate JavaScript step to your script.
  - b. In **Argument > Code** section enter define your variable.

For example, to get data from the server enter `var ws = TC.vtcGetCell("Web Sites",1,"alias");`

3. Select **Toolbox > Functions** and add a **Generic Browser Action** to your script.
4. Enter the variable you defined in Step 2 in **Argument > Location**.

## How to use a VTS API function directly in a step.

You can use the Eval JavaScript code step implement a VTS API in your script. The example



below shows you how to parametrize a URL.

1. Connect to a VTS server
  - a. Select **Toolbox > Miscellaneous** and add an  Evaluate JavaScript step to your script.
  - b. To connect to a VTS, enter `TC.vtcConnect("server", port, "alias")` in the **Arguments > Code** section of the step.
2. Select **Toolbox > Functions** and add a **Generic Browser Action** to your script.
3. Enter `TC.vtcGetCell("Web Sites", 1, "alias")`; in the **Argument > Location** section of the script..

## **How To Create and Use Function and Libraries**

This task describes how to create and use function libraries and functions in TruClient Scripts.

### **Create a function library and function from the TruClient sidebar**


1. Select **Functions** from the drop-down list in the TruClient tab.
2. Select an existing library from the  NewLib drop-down or click the  button from the Function toolbar to create a new library.
3. Click the  button to create a new function. This will insert a new unspecified function.  

4. Click the  button to expand the function.
5. Define the step including function name and end event.
6. Define the function arguments using the **Argument Editor**. Argument names should be meaningful so that when you are using the function it is clear what value you need to specify.
7. Define the transaction using the **Transaction Editor**. For details, ["Transaction Editor Dialog Box \(TruClient\)" on page 550](#).

### **Create a function within a script**

1. Highlight the steps in the script to include in the function. To select multiple steps, press CTRL.
2. Right-click on a highlighted step and select **Group Into > Function** which opens the **Create a New Function** dialog box. For details, see ["Create New Function Dialog Box" on page 549](#).
3. To assign steps that contain arguments, expand the argument section, and insert the function `FuncArgs.<argument name>..`

**Tip:** To insert javascript as the argument value, click the  button to access the Javascript editor.

### Create a global library

1. Select **Function Libraries** from the drop-down from the **TruClient Sidebar**.
2. Select an existing library from the  drop-down in the **TruClient Sidebar**.
3. Click the  button to export the library to a location on your file directory as an xml file.

### Using the copy paste operation in global libraries

Pasting steps that contain test objects from a local script or a local library to a global library creates separate test object that refer to the same UI element. If you change or update one of the test objects in the global library or in the script, you will need to manually update the other test object that refers to the same UI element.

### Examples:

1. Global library "GlobLib" contains step A with a test object "Foo" that relates to the application.  
Script also contains step B with a test object "Foo" that relates to the application.  
If you copy step B and paste it too "GlobLib" there are two different test objects in "GlobLib" that related to "Foo". Therefore, if you change or update one of them you should consider changing the other one manually.
2. Global library "GlobLib" contains Step A with a test object "Foo" that relates to the application.  
Script has steps B and C with a test objects "Foo" that relates to the application. If you copy steps B and C to "GlobLib" there are two different test objects in "GlobLib" that relate to "Foo".

#### Note:

- When working with a global library, you can save changes to the library by clicking the  button.
- If you save the library to a network location, other users can click the  button to import the library.
- Click the  button to disconnect the library from global mode. Any changes that you make in local mode are saved within the script.

### Use a function in the script

1. Click the TruClient **Toolbox** tab.
2. Select the **Functions** tab.
3. Drag and drop **Call Function** to the correct location in your script.
4. Click the **Call Function** link to expand the function.
5. Specify the library and the function in the step section.
6. Specify the arguments' values in the augments section. For details, see "[Create a function within a script](#)" on page 542. (Optional)
7. Specify transactions in the transaction section. (Optional) For details, see "[Transaction Editor Dialog Box \(TruClient\)](#)" on page 550.

## **How to Display Client Side Breakdown Data for TruClient Scripts**

This task describes how to display client side breakdown data associated with transactions in a TruClient Script.

### 1. **Enable Profiling**

Select **Run-time Settings > Replay > Enable Profiling**

### 2. **Create and record a FireFox TruClient script**

For details, see "[How to Develop TruClient Scripts](#)" on page 511

### 3. **Insert transactions**

You can add transactions by using the Transaction Editor. To open the Transaction Editor click the Transaction Editor  button from the Home Tab or click Ctrl + Alt + F7. "[Transaction Editor Dialog Box \(TruClient\)](#)" on page 550


### 4. **Replay script**

## **Results**

A browser window opens displaying the client side breakdown data. For details see, "[TruClient Client Side Breakdown Data](#)" on page 547

## **TruClient Events Handler Editor Dialog Box**

This dialog box enables you to define events handlers and its properties.



<b>To access</b>	Click the  button from the TruClient sidebar.
<b>Important information</b>	Events handlers are designed to handle events that can occur at any time during script replay.
<b>Relevant tasks</b>	<a href="#">" How To Use The Events Handler" on page 536</a> <a href="#">"How To Create and Use Function and Libraries" on page 542</a>
<b>See Also</b>	<a href="#">" TruClient Event Handlers" on page 531</a>

User interface elements are described below:

UI Element	Description
Event Handler Pane	 <b>Add Event Handler.</b> Add an event to the event handler.  <b>Delete Event Handler.</b> Delete an event from the event handler.

UI Element	Description
<b>Properties</b>	<p><b>General</b></p> <ul style="list-style-type: none"> <li>• <b>Name.</b> Enables you to name the event.</li> <li>• <b>Execute only once.</b> Execute the event once.</li> <li>• <b>Allow other handlers to interrupt.</b> Select check box to enable other events to run during the run of this event.</li> </ul> <p>You can select either:</p> <ul style="list-style-type: none"> <li>• <b>Event can be triggered during the entire script.</b> Enable event to be triggered during entire script.</li> </ul> <p>or</p> <ul style="list-style-type: none"> <li>• <b>Start Step.</b> Enables you to select a start step from which point the event handler can be triggered.</li> <li>• <b>End Step.</b> Enables you to select a end step after which the event handler cannot be triggered.</li> </ul> <p><b>Object</b></p> <ul style="list-style-type: none"> <li>• <b>Click to choose an object</b> Enables you to select an object from your application that will trigger the event handler.</li> <li>• <b>Roles.</b> Displays the roles which determines what operations can be done on the object. For example, an “element” role has operations like “click” and “mouse over”. The “textbox” role will also have a “type” operation. Other roles: element, focasable, textbox, check box, filebox, radiogroup, listbox, multi_listbox, slider, datepicker, video, audio, browser.</li> <li>• <b>Name.</b> Enables you to specify the name of the object.</li> <li>• <b>ID Method</b> <b>Automatic (Recommended).</b> Enable TruClient to resolve object identification. <b>XPath.</b> Enables you to insert an xpath query to identify the object <b>JavaScript.</b> Enables you to insert JavaScript code to identify the object.</li> <li>• <b>Related objects.</b> Enables you to associate your object with another object in your application that facilitates object identification during replay.</li> </ul>

UI Element	Description
	<p><b>Event</b></p> <ul style="list-style-type: none"> <li><b>Event type</b></li> </ul> <p>You can select between two event types:</p> <p><b>Object Exists.</b> If object exists during replay, the event handler is triggered.</p> <p><b>Property exists on Object.</b> If the property of an object meets the defined criteria, the event handler is triggered.</p> <p><b>Handler</b></p> <ul style="list-style-type: none"> <li><b>Library.</b> Enables you to select the library containing the function.</li> <li><b>Function.</b> Enables you to select the function.</li> <li><b>Arguments.</b> Enables you to specify the argument values.</li> </ul>

## TruClient Client Side Breakdown Data

The browser window displays client side breakdown information in interactive mode for each transaction in your script.

 TruClient Client Side Breakdown Data					
Transactions	Profiler				
Name	JS Time (ms)	Network Time (ms)	Wait Time (ms)	Total Time (ms)	
OptionSelection	587.652	9938	4654	24309	
<b>Important Information</b>	<ul style="list-style-type: none"> <li>Select <b>Run-time settings &gt; Replay &gt; Enabling profiling</b> before you replay your script.</li> <li>If you create a Controller scenario with your script, the Client Side Breakdown results can be viewed in Analysis. For details, see "<a href="#">"Client Side Breakdown (Over Time) Graph" on page 1519</a> or "<a href="#">"Client Side Java Script Breakdown (Over Time) Graph" on page 1520</a></li> </ul>				
<b>Relevant tasks</b>	<a href="#">"How to Display Client Side Breakdown Data for TruClient Scripts " on page 544</a>				

User interface elements are described below:

### Client Side Breakdown

UI Element	Description
------------	-------------

**Client Side Breakdown, continued**


<b>JS Time</b>	<p><b>Measured JavaScript run time</b></p> <p>The following data elements are returned for each transaction:</p> <p><b>Name.</b> The function name.</p> <p><b>File.</b> The name of the JS file where the function exists.</p> <p><b>Calls.</b> Log of the execution stack and drill down to the function calls during the transaction.</p> <p><b>Total Execution Time.</b> Time elapsed after each function call including its inner function calls.</p> <p><b>Total Own Execution Time.</b> Time elapsed after each function call excluding its inner function calls.</p> <p><b>Max Recuse Depth.</b> Function's maximum calling stack depth.</p> <p><b>Min Execution Time.</b> Function's minimum run time including its inner function calls.</p> <p><b>Max Execution Time.</b> Function's maximum run time including its inner function calls.</p> <p><b>Min Own Execution Time.</b> Function's minimum run time excluding its inner function calls.</p> <p><b>Max Own Execution Time.</b> Function's maximum run time excluding its inner function calls.</p>
<b>Network Time</b>	<p><b>Measured network activity</b></p> <p>The following data elements are returned:</p> <p><b>URL.</b> The URL of the page resource.</p> <p><b>Start Time.</b> Start time of the transaction on the network</p> <p><b>End Time.</b> End time of the transaction on the network.</p> <p><b>Duration.</b> Total duration of the transaction on the network.</p>

**Client Side Breakdown, continued**

<b>Wait Time</b>	<p><b>Wait time during transaction</b></p> <p>Wait time is defined as pacing + minimum time + wait step.</p> <p>The following data elements are returned for each transaction:</p> <ul style="list-style-type: none"> <li><b>Start.</b> Start time of wait time.</li> <li><b>Type.</b> Either pacing, minimum time, or wait step.</li> <li><b>End.</b> End time of wait time.</li> <li><b>Duration.</b> Total wait time duration measured in milliseconds.</li> </ul>
<b>Total Time</b>	<p>Total transaction time (in milliseconds) = JS + Network + Wait</p> <p><b>Note:</b> JS + Network or Network + Wait can overlap so, Total Time it might not be the sum of JS + Network + Wait.</p>

**Create New Function Dialog Box**

This dialog box enables you create a new function and assign the function to a library.




<b>To access</b>	Right click on a highlighted step in the script, and then select <b>Group Into &gt; New Function</b> .
<b>Relevant tasks</b>	<a href="#">"How To Create and Use Function and Libraries" on page 542</a>

User interface elements are described below:

UI Element	Description
<b>Function Name</b>	Enables you to specify a function name.
<b>Add to library</b>	<ul style="list-style-type: none"> <li><b>Select Existing.</b> Save new function to an existing library.</li> <li><b>Create New.</b> Save new function to a new library.</li> </ul>
<b>Replace steps with function call</b>	If selected, TruClient will automatically insert a call function in place of steps.

## Transaction Editor Dialog Box (TruClient)

This dialog box enables you to manage transactions in TruClient Vuser scripts.



<b>To access</b>	Click on the  from the <b>TruClient Sidebar</b>
<b>Important information</b>	If you add a wait step inside a transaction in an TruClient Script, the log will detail think time which is equal to wait time + pacing time + max(minimum time).

User interface elements are described below:

UI Element	Description
	Adds a new transaction or deletes the selected transaction.

<b>General</b>	Enables you to edit the name of the transaction.
<b>Start Point</b>	<p>The step and the event which marks the start of the transaction. An event can be one of the following:</p> <ul style="list-style-type: none"> <li>• <b>Step started.</b> The first event triggered when a step starts running. The event triggered before the step action has started running and before any other activity takes place.</li> <li>• <b>Action started.</b> This event occurs immediately after the <b>Step started</b> event and signifies that the action to be performed has started. For example, the action might be navigation to a URL or a button click.</li> <li>• <b>Action completed.</b> This event is triggered when the action to be performed has completed. However, the step may not have ended yet. For example, for steps related to the application, there might be additional network or DOM activity.</li> <li>• <b>Step synchronous network completed.</b> Step ends when all HTTP requests have been completed excluding requests that are associated with open connections that are not relevant to the step. Usually, these requests are triggered by using XMLHttpRequest.</li> <li>• <b>DOM content loaded.</b> Step ends when the page's Document Object Model (DOM) is ready. This means that the API for interacting with the content, style and structure of a page is ready to receive requests from your application client side code.</li> <li>• <b>Document load.</b> Step ends when the process of loading a document is completed. This means that all scripts and stylesheets have finished loading and have been executed, and all images have been downloaded and displayed.</li> <li>• <b>Dialog opened.</b> Step ends when a dialog box is opened.</li> <li>• <b>Step completed.</b> This event is triggered as soon as the work inside the step container has completed. It is triggered only if the step completed successfully.</li> <li>• <b>After step ended.</b> The last event in the events chain, it occurs after <b>Step completed</b>, but unlike <b>Step completed</b> it will be triggered regardless if the step was completed successfully or not.</li> </ul>

<b>End Point</b>	<p>The step and the event which marks the end of the transaction. An event can be one of the following:</p> <ul style="list-style-type: none"><li>• <b>Step started.</b> The first event triggered when a step starts running. The event triggered before the step action has started running and before any other activity takes place.</li><li>• <b>Action started.</b> This event occurs immediately after the <b>Step started</b> event and signifies that the action to be performed has started. For example, the action might be navigation to a URL or a button click.</li><li>• <b>Action completed.</b> This event is triggered when the action to be performed has completed. However, the step may not have ended yet. For example, for steps related to the application, there might be additional network or DOM activity.</li><li>• <b>Step synchronous network completed.</b> Step ends when all HTTP requests have been completed excluding requests that are associated with open connections that are not relevant to the step. Usually, these requests are triggered by using XMLHttpRequest.</li><li>• <b>DOM content loaded.</b> Step ends when the page's Document Object Model (DOM) is ready. This means that the API for interacting with the content, style and structure of a page is ready to receive requests from your application client side code.</li><li>• <b>Document load.</b> Step ends when the process of loading a document is completed. This means that all scripts and stylesheets have finished loading and have been executed, and all images have been downloaded and displayed.</li><li>• <b>Dialog opened.</b> Step ends when a dialog box is opened.</li><li>• <b>Step completed.</b> This event is triggered as soon as the work inside the step container has completed. It is triggered only if the step completed successfully.</li><li>• <b>After step ended.</b> The last event in the events chain, it occurs after <b>Step completed</b>, but unlike <b>Step completed</b> it will be triggered regardless if the step was completed successfully or not.</li></ul>
------------------	---

# The TruClient Sidebar

## ***TruClient Home Tab***

This tab enables you to control the basic flow of the recording process for TruClient scripts.

### **Actions**



<b>To access</b>	Select <b>Action</b> from the drop-down list on the TruClient sidebar.
<b>Relevant tasks</b>	<a href="#">"TruClient Step Structure" on page 502</a>

User interface elements are described below:

UI Element	Description
	<b>Record.</b> Starts recording the script. Additionally, you can use the arrow to specify whether to record before or after the selected step.
	<b>Play.</b> Replays the script. Additionally, you can use the arrow to specify whether to play the selected step only, or to run the script step by step. Running the script step by step pauses the replay after each step. For more information, see <a href="#">"How to Debug TruClient Scripts" on page 517</a> .
	<b>Stop.</b> Stops recording or replaying the script.
	<b>Toggle Breakpoint.</b> Toggles breakpoints on the selected step.
	<b>Script Level.</b> Modifies the script levels that are visible and replayed in the script. For more information, see <a href="#">"TruClient Script Levels" on page 515</a> .
	<b>Start/End Transaction.</b> Inserts a starting or ending point for a transaction.
	<b>Transaction Editor.</b> Opens the Transaction Editor, allowing you to define new transactions and modify existing ones.
	<b>Save.</b> Saves the script.
	<b>General Settings.</b> Opens the General Settings dialog box. For details, see <a href="#">"TruClient General Settings Dialog Box" on page 562</a> .

	<p><b>Snapshot View.</b> Displays the Snapshot view in the right pane. Adds the following elements to the right pane:</p> <ul style="list-style-type: none"> <li>• <b>Snapshot Type.</b> These buttons enable you to view snapshots taken during different modes: <ul style="list-style-type: none"> <li>▪ <b>Recording.</b> Display snapshots that were taken for a specific step during recording.</li> <li>▪ <b>Interactive Replay.</b> Display snapshots that were taken for a specific step during interactive replay.</li> <li>▪ <b>Load Mode Replay.</b> Display snapshots that were taken for a specific step during load mode replay</li> <li>▪ <b>Play Slide Show.</b> Display snapshots as a slide show.</li> <li>▪ <b>Stop Slide Show.</b></li> </ul> </li> <li>• <b>View.</b> You can select from the following views: <ul style="list-style-type: none"> <li>▪ <b>Single.</b> Displays the snapshot for a single step.</li> <li>▪ <b>Compare.</b> Splits the screen so you can compare snapshots from different modes. Use the Snapshot View buttons in each pane to select which snapshots to view. Click the <b>Synchronize Scrolling</b> button  to synchronize scrolling between the panes. The snapshot error icon  indicates that the snapshot is not current for the step.</li> <li>▪ <b>Thumbnails.</b> Displays the snapshots in thumbnails view.</li> </ul> </li> <li>•  <b>Previous/Next.</b> Navigates to the screenshot for the previous or next step. The corresponding step is highlighted in the script.</li> </ul>
	Opens the Event Handler Editor box. For details, see " <a href="#">TruClient Events Handler Editor Dialog Box</a> " on page 544

## Functions



<b>To access</b>	Select <b>Functions</b> from the drop-down list on the <b>TruClient Sidebar</b>
<b>Relevant tasks</b>	<a href="#">"How To Create and Use Function and Libraries" on page 542</a>

User interface elements are described below:

UI Element	Description
------------	-------------

 NewLib	Enables you to select the active library.
	<b>New Library.</b> Enables you to create a new library.
	<b>Import Library.</b> Import a function library from an xml file.
	<b>Export Library.</b> Export a function library to an xml file.
	<b>Delete Library.</b> Delete a function library.
	<b>New Function.</b> Enables you to create a new function. For details, see " <a href="#">How To Create and Use Function and Libraries</a> " on page 542

## Context Menu

<b>To access</b>	Select a step and right click to display the context menu.
<b>Relevant tasks</b>	<a href="#">"TruClient Step Structure" on page 502</a>

UI Element	Description
<b>&lt;Replay Actions&gt;</b>	<p><b>Play This Step.</b> Replay the selected step only.</p> <p><b>Play From This Step.</b> Replay the script from the selected step.</p>
<b>&lt;Record&gt;</b>	<ul style="list-style-type: none"> <li><b>Before step.</b> Insert the next set of recorded steps before the selected step.</li> <li><b>Into Step.</b> Insert the next set of recorded steps into the selected group.</li> <li><b>After Step.</b> Insert the next set of recorded steps after the selected step.</li> </ul>
<b>Toggle Breakpoint</b>	Insert/Remove a toggle breakpoint.
<b>&lt;Transaction Steps&gt;</b>	<ul style="list-style-type: none"> <li><b>Start Transaction.</b> Insert a Start Transaction step into the script.</li> <li><b>Surround With Transaction.</b> Insert a Start Transaction and End Transaction steps around a single or multiple steps into the scripts.</li> <li><b>End Transaction.</b> Insert an End Transaction step into your script.</li> </ul>

<b>&lt;Group Actions&gt;</b>	<p><b>Group Steps</b> Multiple steps are grouped together as a single step.</p> <p><b>Group Into</b> Multiple steps are group into:</p> <ul style="list-style-type: none"> <li>• <b>If Clause.</b> A logical structure that controls the flow of your script.</li> <li>• <b>For Loop Clause .</b> A logical structure that repeats the steps contained in the loop a specified number of times.</li> <li>• <b>New Function.</b> A group of steps, such as a login, that you define as a function</li> </ul>
<b>&lt;Edit Actions&gt;</b>	<ul style="list-style-type: none"> <li>• <b>Cut.</b> Cut select step from the script.</li> <li>• <b>Copy.</b> Copy selected step in the script.</li> <li>• <b>Paste.</b> Paste selected step into the script.</li> </ul>
<b>Delete</b>	Delete a step from the script.
<b>Disable/Enable</b>	Toggle between disabling or enabling a step during replay.
<b>Edit Step</b>	Expand the step to display step, argument and transaction properties.
<b>Show</b>	<p><b>Step Numbers.</b> Display step numbers.</p> <p><b>Animations.</b> Enable/disable step animation in the TruClient sidebar.</p>

## TruClient Edit Tab

This tab enables you to cut, copy, and paste steps and data in TruClient scripts.



<b>To access</b>	Select the Edit tab from the <b>TruClient sidebar</b> .
------------------	---

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
	Cut the selected data or step.
	Copy the selected step or data.

	Pastes before the selected step.
	Pastes after the selected step.
	Pastes into the selected step.
	Deletes the selected step
	<p>Opens the Find dialog box, allowing you to search the script for steps by step name or number.</p> <p><b>Note:</b> You can create a step that is a group of sub-steps. If you are searching for step that is a sub-step, you need to specify both the step group number and sub-step number. For example, enter 4.1 to search for the first sub-step in the fourth (group) step .</p>
	Go to the specified step.
	<p>The following actions can be undone:</p> <ul style="list-style-type: none"> <li>• Cut</li> <li>• Copy</li> <li>• Paste</li> <li>• Delete</li> <li>• Group • Drag &amp; drop (step)</li> <li>• Add step from the toolbox</li> </ul>
	<p>The following actions can be redone:</p> <ul style="list-style-type: none"> <li>• Cut</li> <li>• Copy</li> <li>• Paste</li> <li>• Delete</li> <li>• Group • Drag &amp; drop (step)</li> <li>• Add step from the toolbox</li> </ul>


## **Window Tab**



This tab enables you to control multiple browser windows for the same script. Select the window that contains the application that you want to bring to focus. This is needed for the debugging phase of script development, for example, when attempting to highlight a step object.

## **TruClient Toolbox**

The toolbox contains all of the steps that you can add to a TruClient script. The toolbox opens and closes by clicking on the tab, and moves by dragging it up or down.



User interface elements are described below:

UI Element	Description
------------	-------------

<b>Functions</b>	<ul style="list-style-type: none"> <li>• <b>Verify.</b> Verify that an object exists in the application.</li> <li>• <b>Wait.</b> Wait for a specified number of seconds before continuing with the next step.</li> <li>• <b>Wait for Object.</b> Wait for an object to load before continuing with the next step.</li> <li>• <b>Generic Object/Browser Action.</b> Blank steps that can be inserted and manually configured.</li> <li>• <b>Call Function.</b> Insert a custom function in the script. For details, see "<a href="#">How To Create and Use Function and Libraries</a>" on page 542.</li> </ul>
<b>Flow Control</b>	<ul style="list-style-type: none"> <li>• <b>For Loop.</b> A logical structure that repeats the steps contained in the loop a specified number of times.</li> <li>• <b>If Block.</b> A logical structure that runs the steps contained in the block if the condition is met.</li> <li>• <b>Add else.</b> Click the <b>Add else</b> link to add an <b>else</b> section to your <b>If</b> block. If the condition is not met, the steps included in the <b>else</b> section run.</li> <li>• <b>Remove else.</b> Removes the <b>else</b> section from the <b>If</b> block.</li> </ul> <p><b>Note:</b> If the <b>else</b> section contains steps and you click <b>Remove else</b>, the steps are deleted. Copy and paste them into the main body of your script to save them.</p> <ul style="list-style-type: none"> <li>• <b>If exists.</b> A combination of "If Block" and "Verify", a logical structure that runs the steps contained in the block if the condition on a property of the selected object is met.</li> <li>• <b>If verify.</b> A logical structure that runs the steps contained in the block if the selected object exists in the application.</li> <li>• <b>Break.</b> Causes the loop to end immediately without completing the current or remaining iterations.</li> <li>• <b>Continue..</b> Causes the current loop iteration to end immediately. The script continues with the next iteration.</li> <li>• <b>Catch Error.</b> Catches an error in the step immediately preceding and runs the contents of the catch error step. For more information, see "<a href="#">How to Enhance TruClient Scripts</a>" on page 534.</li> <li>• <b>Exit.</b> Exits the iteration or the entire script depending on the specified setting.</li> </ul>

<b>Miscellaneous</b>	<ul style="list-style-type: none"> <li>• <b>Evaluate JavaScript.</b> Runs the JavaScript code contained in the step.</li> <li>• <b>Evaluate JS on Object.</b> Runs the JavaScript code contained in the step after the specified object is loaded in the application.</li> <li>• <b>Evaluate C.</b> Runs the C code contained in the step.</li> <li>• <b>Comment.</b> A blank step which allows you to write comments in your script.</li> <li>• <b>Rendezvous.</b> Synchronize all Vusers in a Controller scenario to run a specified step at the same time. For example, you may want to test the impact of several users logging into your application at the same time.</li> </ul> <p><b>Note:</b> To insert a rendezvous step, drag it from the toolbox and place it above the step you want to synchronize.</p>
----------------------	---

## Browsers in TruClient

This section includes:

### **General Browser Settings (TruClient)**

Each TruClient script is opened in a browser with a different profile. The browser profile saves user data such as cookies, client certificates, history, cache, and so on. Make the changes in the browser when interactively developing the script using TruClient. These changes will only apply to the current script.

Browser options that affect interactive mode can be modified in the **TruClient General Settings** dialog box. All of the settings in this dialog box are imported to each new script as it is created, but only affect interactive mode. When the script is saved, these settings are also copied to the run-time settings as well.

Scripts that are run in load mode use the settings defined in the **Load > Browser Settings** node of **Run-time Settings** dialog box. For details, see "[Load > Browser Settings Node \(Ajax TruClient\)](#)" on page 338.

The Firefox extensions settings are imported to each script every time a script is opened in Firefox. For details, see "[TruClient General Settings Dialog Box](#)" on page 562.

Some standard browser options are disabled. These include, but are not limited to, some File, Bookmark, Tools, and Help options. To save bookmarks for use in your scripts, use the "[TruClient General Settings Dialog Box](#)" on page 562.

### **Private Browsing (TruClient)**

Private Browsing is a browser mode which allows you to browse without saving information about your session. Some examples of items which are not saved are passwords, cookies, and history.

To more accurately emulate real users, TruClient replays scripts in private browsing mode. This ensures that the browser does not use saved session information when running a script more than one time.

## **TruClient Browser for IE**

The TruClient Browser for IE simulates the functionality of an IE browser. This enables you to record and replay scripts as if you were working in an IE environment.

**Note:** The TruClient for IE protocol is designed to work with applications running in standard mode only.

The TruClient engine depends on specific browser features, available in IE 9 or higher versions, that are not supported by Internet Explorer prior to version 9 and are also not supported in IE9 if backward compatibility mechanisms are in use.

For details on document and browser modes, see [Browser modes](#).

**Note:** The TruClient browser for IE also requires read access to the following registry key:  
HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Internet Explorer

### **Firebug Lite**

Firebug Lite is a third-party utility that provides many valuable development tools. You can edit, debug, and monitor CSS, HTML, and JavaScript live in any web page. You can access this utility by selecting **Advanced > FireBug Lite** or by pressing **F12** while in TruClient's IE browser.

For details on FireBug Lite's features, see [What is Firebug?](#)

### **Enforce Standard Mode**

TruClient for IE can only record and replay application in standard mode. TruClient enforces this mode on all pages that you navigate to while you are recording and replaying.

If you wish to explore how pages are rendered in a non-standard IE mode, you can temporarily deactivate enforcement by deselecting **Advanced > Enforce Standard Mode**. When deselected the following message appears in the Sidebar:

#### **TruClient for LoadRunner**

TruClient IE can only record applications that were designed to display in IE9 or IE10 Standards mode. Standards mode is not being enforced and the script cannot be developed. To enforce Standards mode, select 'Advanced' > 'Enforce Standard Mode' or click the 'Enforce' button

**Enforce**

While in the mode you will not be able to develop or edit scripts in the TruClient IE browser. Click the **Enforce** button in the message box or select **Advanced > Enforce Standard Mode**, to continue recording and replaying in the TruClient for IE browser.

## **TruClient General Settings Dialog Box**

This dialog box enables you to set many options that affect the browser as you develop your scripts in interactive mode.

### **General settings**

<b>To access</b>	TruClient General Settings button 
<b>Important information</b>	The TruClient General Settings dialog box can be accessed from the VuGen window or the TruClient sidebar in interactive mode.
<b>Relevant tasks</b>	<a href="#">" How to Develop TruClient Scripts" on page 511</a>

### **Browsing Settings Tab**

This tab enables you to configure settings for the TruClient browser for scripts that you run in interactive mode.

The settings available in the Browser Settings tab are the same settings that are available in VuGen's **Run-Time Settings > Load > Browser Settings** node. For a description of the available options, [" Load > Browser Settings Node \(Ajax TruClient\)" on page 338](#).

Settings that you modify in the Browsing Settings tab affect interactive mode only and apply to all TruClient scripts. When you save your script in interactive mode, any settings that you modified in the Browsing Settings tab are applied to the Load Mode Browser settings.

 Firefox Options
<b>Tab</b>

Interactive Options Tab	UI Element	Description
	<b>Action on Error</b>	<p><b>Abort Script.</b> Abort script on error.  <b>Continue to the next iteration.</b> Stop iteration on error and continue to next iteration.</p>
	<b>Snapshots generation</b>	<p><b>Recording snapshots generation</b></p> <ul style="list-style-type: none"> <li>• <b>Never.</b> Never generate snapshots during recording.</li> <li>• <b>Always.</b> Always generate snapshots during recording.           <ul style="list-style-type: none"> <li>▪ <b>Maximum Level.</b> Enables you to select the script level to generate snapshots (1-3).</li> </ul> </li> </ul> <p><b>Replay snapshots generation</b></p> <ul style="list-style-type: none"> <li>• <b>Never.</b> Never generate snapshots during replay.</li> <li>• <b>On error.</b> Generate snapshots during replay on error.</li> <li>• <b>Always.</b> Always generate snapshots during replay.</li> </ul>
	<b>Object Identification Assistant</b>	<p><b>Enable.</b> If selected, enables the object identification assistant.            The object identification assistant facilitates resolving identification errors during replay. For details, see "<a href="#">How to Resolve Object Identification Issues</a>" on page 519.</p>
	<b>Server Parameter</b>	<p><b>Replace server with parameter.</b> If selected, server domain name in navigation steps will be automatically replaced by a parameter.</p>
	<b>Console Settings</b>	<p><b>Display log messages.</b> Display console's log messages during replay.</p>
	<b>Debug Settings</b>	<p><b>Disable Step Into Functions.</b> Disable display steps of functions during interactive replay.</p>
<b>Encryption Tab</b>	For configuration details, see <a href="#">Mozilla Support for Encryption</a> .	
<b>Extension Tab</b>	For configuration details, see <a href="#">Mozilla Support for Extensions</a>	



## Internet Explorer Options

### Interactive Options Tab

User interface elements are described below:

UI Element	Description
<b>Action on Error</b>	<p><b>Abort Script</b> Abort script on error.  <b>Continue to the next iteration.</b> Stop iteration on error and continue to next iteration.</p>
<b>Snapshots generation</b>	<p><b>Recording snapshots generation</b></p> <ul style="list-style-type: none"> <li>• <b>Never.</b> Never generate snapshots during recording.</li> <li>• <b>Always.</b> Always generate snapshots during recording.           <ul style="list-style-type: none"> <li>▪ <b>Maximum Level.</b> Enables you to select the script level to generate snapshots (1-3).</li> </ul> </li> </ul> <p><b>Replay snapshots generation</b></p> <ul style="list-style-type: none"> <li>• <b>Never.</b> Never generate snapshots during replay.</li> <li>• <b>On error.</b> Generate snapshots during replay on error.</li> <li>• <b>Always.</b> Always generate snapshots during replay.</li> </ul>
<b>Object Identification Assistant</b>	<p><b>Enable.</b> If selected, enables the object identification assistant.</p> <p>The object identification assistant facilitates resolving identification errors during replay. For details, see "<a href="#">How to Resolve Object Identification Issues</a>" on <a href="#">page 519</a>.</p>
<b>Server Parameter</b>	<p><b>Replace server with parameter.</b> If selected, server domain name in navigation steps will be automatically replaced by a parameter.</p>

#### Client Certificate Tab

Enables you to manually export the client certificate to the script folder .

## TruClient - Troubleshooting and Limitations (General)

This section describes troubleshooting and limitations for TruClient scripts and other fun things.

## **Troubleshooting Communication between VuGen and TruClient**

**Error message: VuGen cannot open the TruClient browser because the port range is busy or invalid.**

**Recommendation:** In order to open a server, a free port is needed. The server is open on the `http://127.0.0.1:<free_port>/` url.

The free port can be configured in the following xml files :

```
%APPDATA%\Hewlett-Packard\LoadRunner\Data\Settings\VuGenProperties.xml  
<VuGenProperties>  
  <BrowserCommunicationServerEndPort value="8090" />  
  <BrowserCommunicationServerStartPort value="8080" />
```

The default port range is between 8080 through 8090. If there is a problem with the ports (all ports are busy or the start port is bigger than the end port) you can change the range in the configuration file.

If you are unable to resolve this issue contact HP software support.

**Error Message: VuGen cannot open the TruClient browser.This error has occurred because you do not have the proper permissions to establish communication between VuGen and the TruClient browser.**

**Recommendation:** Ask your administrator or a power user to run this command:

```
netsh http add urlacl url=http://127.0.0.1:<port_given_in_the_error_message>/  
user=<DOMAIN>\<USER_NAME>
```

Example: `netsh http add urlacl url=http://127.0.0.1:8080/ user=DOMAIN\john`

## **Word Verification Function in the Business Process**

Many web sites use special Word Verification fields that display some text that the user must enter in order to validate that an actual user is filling out the form.

This is designed to block crawlers, spiders and so on from using the site and taking up valuable system resources.

These fields are especially designed to block automatic tools such as LoadRunner.

In order to complete your business process automatically you must cancel this function on the web site against which you are running the load.

## Protocol Limitations

### McAfee Anti-virus causes Vusers to stop running in Load Mode

**Issue:** Newer versions of McAfee Anti-virus may cause network hook collision with the TruClient for IE protocol. You may experience unexpected behavior during load. For example, some of your Vusers may stop running. As a result, an error message will appear in the **Controller > Scenario Status > Errors** pane and the Vuser status displays as Failed.

**Steps to resolve:** Disable McAfee.

### Flash, Silverlight, ActiveX limitation for TruClient IE

User actions on UI elements that are based on Flash, Silverlight, ActiveX in general and Java applets technologies are currently not recorded and replayed.

### Java applets and Silverlight limitation for TruClient FF

User actions on UI elements that are based on Java applets and Silverlight technologies are currently not supported for record and replay.

- When you view Web page component breakdown graphs for TruClient Vusers, TruClient measurements might not be available or might be less accurate than those of other protocols. For example the Time to First Buffer Breakdown graph, and measurements such as SSL Handshake, and Client/Error Time might not be available.
- TruClient is a UI based protocol therefore while running a TruClient script in Controller you might encounter an exception: "Failed to Initialize. Reason TimeOut". It is recommend to increase the **Init time out**. (**Controller > Tools > Options**)to provide the Vusers with additional time to finalize the initialization stage.
- After opening TruClient by clicking Develop Script, and subsequently closing it, VuGen may still display the yellow banner of Develop mode. **Workarounds:** If working with a proxy, you must specify "bypass local connections". If working with a PAC file, the PAC must specify a direct connection for 127.0.0.1
- If you edit a TruClient script using a later version of LoadRunner than the one on which you recorded the script, it may fail to replay in some cases.  
Before modifying the script, save a backup copy of the script. **Workaround:** If the replay fails, re-record the script using the latest version of the TruClient protocol.
- TruClient will not record "mouse overs" when the element has a CSS rule of "Mouse Hover". **Workaround:** Instead of mouse hovering, click the elements to open the drop down (the clicks are recorded).
- TruClient protocol step types and arguments are not localized.
- TruClient General Strings are not localized in the Japanese version.

#### TruClient - IE Protocol

- The TruClient - IE protocol does not support Diagnostics for J2EE/.NET.
- When recording a script in TruClient -IE protocol, a keyboard event together with the Ctrl key is not supported and therefore not recorded.
- TruClient - IE protocol requires Internet Explorer 9 or 10 to be installed on the load generator.
- Due to Internet Explorer 9 behavior, when using TruClient - IE protocol with Internet Explorer 9, and you have a JRE plug-in that is older than version 7, the browser may crash when you visit web pages that are rendered and contain applets that need to instantiate the plug-in.

**Workaround:** Install the JRE 7 plug-in or a later version.

- TruClient supports only IE9 or IE10 Standard modes.

#### TruClient - Firefox Protocol

- Security warning dialog boxes are not displayed in TruClient during script development.
- If you encounter problems when running TruClient - Firefox Vusers in load mode, modify the **Pacing settings (Replay > Run-Time Settings > General > Pacing)** as follows: Select either **After the previous iteration ends**, or **At <fixed/random> intervals**.
- The TruClient - Firefox protocol can only be used with applications that support the Mozilla Firefox browser.
- TruClient - Firefox does not support Kerberos authentication. If the server also supports NTLM, TruClient will automatically move the authentication to NTLM and continue working.

## Converting a TruClient Script to a Web HTTP/HTML Script

Combine the advantage of fast script development and the advantage of running many Vusers by converting a TruClient script to a Web HTTP/HTML script.

#### Note:

You will need to have an understanding of the Web HTTP/HTML protocol to successfully replay the script.

During the conversion, comments and APIs are added to the Web HTTP/HTML protocol script that document the conversion process.

1. Create a TruClient script. For details, see "[How to Develop TruClient Scripts](#)" on page 511
2. Save the script and close the TruClient Side Bar.

3. From VuGen toolbar, click the  Convert button to convert the script.
4. After the script is generated, review the script, keeping in mind that the Web HTTP/HTML protocol records on the transport level. For example, you may need to address correlation or parameter issues in your converted script. For details, see [Web \(HTTP/HTML\) Protocol - Overview](#).

### Limitations

Conversion of TruClient scripts to Web HTTP/HTML scripts does not support converting steps that call 127.0.0.1 (localhost) address.

## LR Function Reference

This section includes:

### ***TruClient Functions***

The following functions can be inserted as values in TruClient step elements.

Method	Description	Arguments
The arguments in this row can be used in all methods		<ul style="list-style-type: none"> <li>• <b>object</b>. The step's object as defined in the application.</li> <li>• <b>window</b>. Points to the global window object of the application.</li> <li>• <b>document</b>. The global document object of the application.</li> </ul>
IO.createDir(path)	Creates the specified folder. If needed, creates all the folders necessary to complete the path.	<b>path</b> . The absolute path of the folder.
IO.delete(path)	Deletes the specified folder or file. If a folder is specified, deletes all the files in the folder, including sub-directories.	<b>path</b> . The absolute path of the folder or file.
IO.isExist(path)	Returns True if the specified folder or file exists and False if it does not. Returns False for a disconnected or unauthenticated mapped drive.	<b>path</b> . The absolute path of the folder or file.
IO.read(path, charset)	Returns all the data from the specified file. Converts the data from the specified charset to unicode.	<b>path</b> . The absolute path to the file. <b>charset</b> . The charset of the file, if it is not UTF 8.

Method	Description	Arguments
IO.write(path, string, append, charset)	Writes the string to the specified file. If the file does not exist it is created.	<b>absolute path.</b> The absolute path to the file. <b>string.</b> The string to write to the file. <b>append.</b> Boolean. <b>True.</b> (default) Append the string to the end of the file. <b>False.</b> Overwrite the file with the string. <b>charset.</b> The charset of the file, if it is not UTF 8.
LR.advanceParam (parameter)	Advances the specified parameter to the next value in the file.	<b>parameter.</b> The name of the parameter to advance. Must be a parameter of type file or unique number.
LR.getUserIP	Returns the IP address when IP spoofing is enabled and the script is running in load mode in Controller.	
LR.setParam(name, value)	Saves a string to a parameter, creating the parameter if it does not exist.	<b>name.</b> The name of the parameter in which to save the value. <b>value.</b> The value.
LR.crossTransactionStart (name,value)	Begins a transaction in a Vuser script that will be ended in another Vuser script.	<b>name.</b> The name of the transaction. <b>value.</b> A pointer to a parameter list.
LR.crossTransactionEnd (name,value,status)	Ends a transaction in a Vuser script that has been started in another Vuser script.	<b>name.</b> The name of the transaction. <b>value.</b> A pointer to a parameter list. <b>status.</b> One of the following:"Pass" or "Fail".
LR.transactionDuration (name)	Returns the duration of a specific transaction.	<b>name.</b> The name of the transaction
LR.getParam(name)	Returns the value of the specified parameter.	<b>name.</b> The parameter name.
LR.getLRAAttr(name)	Returns the value of the specified mdrv command parameter.	<b>name.</b> The name of the command-line parameter.
LR.evalC(funcname)	Runs the specified function whose definition is found in the specified file.	<b>funcname.</b> The function name.  Use the #include command to include the file where the function is defined.

Method	Description	Arguments
LR.log(text, level)	Logs a message.	<p><b>text.</b> The message.  <b>level.</b> One of the following:</p> <ul style="list-style-type: none"> <li>• "Error",</li> <li>• "Warning",</li> <li>• "Standard",</li> <li>• "Extended",</li> <li>• "Status". The LR.log level= Status sends a string to the Status area of the Controller. It also sends the string to the Vuser log. When run from VuGen, the message is sent to output.txt.</li> </ul> <p><b>example:</b> LR.log("text", "Error");</p>
LR.decrypt(text)	Returns the text after decryption.	<b>text.</b> The encrypted text.
LR.userDataPoint(name, value)	Records a user-defined data point for analysis.	<p><b>name.</b> The name of the data point. Do not begin a data-point name with any of these strings: HTTP, NON_HTTP, RETRY, mic_, stream_, mms_</p> <p><b>value.</b> The numeric value.</p>
evalXPath(XPath)	Returns an array of the objects defined by the XPath in the argument.	<b>xpath.</b> The xpath query.
LR.startTransaction(name)	Starts a LoadRunner transaction.	<b>name.</b> The name of the transaction to start.
LR.endTransaction(name, status)	Ends a LoadRunner transaction.	<ul style="list-style-type: none"> <li>• <b>name.</b> The name of the transaction to end</li> <li>• <b>status.</b> One of the following values: "Pass", "Fail", "Auto"</li> </ul>
LR.vuserStatusMessage(string)	Indicates which Vuser is handling a specific script.	<p><b>string.</b> Any string.</p> <p><b>Example:</b> LR.vuserStatusMessage ("FlightStatus")</p>
Utils.clearCookies()	Removes all cookies currently stored by the Vuser.	
Utils.clearCache()	Clears the contents of the cache simulator.	
Utils.getEnv(name)	Returns the value of the specified environment variable. Returns an empty string if the specified variable does not exist.	<b>name.</b> The name of the environment variable.

Method	Description	Arguments
Utils.import(path)	Evaluates the specified JavaScript file in the arguments context.	<b>path.</b> The absolute path to the JavaScript file.
Utils.isEnvExists(name)	Returns <b>True</b> if the specified environment variable exists and <b>False</b> if it does not exist.	<b>name.</b> The name of the environment variable.
Utils.setEnv(name, value)	Sets the named environment variable to the specified value. If the variable already has a value it is overwritten.	<ul style="list-style-type: none"> <li>● <b>name.</b> The name of the environment variable.</li> <li>● <b>value.</b> The value to set the environment variable to.</li> </ul>
Utils.addAutoFilter(filter, isIncluded)	Adding a filter to one of the black list or white list lists of URLs. The URL of each HTTP request will be checked against those lists – first the black list, and if not empty, the white list. HTTP requests that do not pass the check will be blocked.	<ul style="list-style-type: none"> <li>● <b>filter.</b> String representing the URL.</li> <li>● <b>isInclude.</b> True value indicates the white list, false otherwise.</li> </ul>
Utils.removeAutoFilter(filter, isIncluded)	Remove a filter from one of the black list or white list lists of URLs.	<ul style="list-style-type: none"> <li>● <b>filter.</b> String representing the URL.</li> <li>● <b>isInclude.</b> True value indicates the white list, false otherwise.</li> </ul>
Utils.cleanupAutoFilters()	Remove all filters from both the black list and white list lists of URLs.	
Utils.addAutoHeader(header, value, merge)	Adding an HTTP header to every consecutive HTTP requests following this function call.	<ul style="list-style-type: none"> <li>● <b>header.</b> The name of the header to be added.</li> <li>● <b>value.</b> The value of the header to be added.</li> <li>●  <b>merge.</b> True value indicates to merge the value with an existing header by the same name, false indicates to overwrite it.</li> </ul>
Utils.removeAutoHeader(header)	Stops the adding of an HTTP header to every consecutive HTTP request following this function call.	<b>header.</b> The name of the header to be stopped from being added.
Utils.cleanupAutoHeaders()	Removes all HTTP headers and stops adding HTTP headers to every consecutive HTTP request following this function call.	

## TruClient VTS Functions

The following functions can be inserted as values in TruClient step elements.

Method	Description	Arguments	Notes about function behavior
LR.vtcAddCell(colName, value, VtsName)	Sets the last field of a column to a value.	<b>colName.</b> The name of the column.  <b>value.</b> The value as a string.  <b>VtsName.</b> The alias of the VTS server.	If the column specified in the argument does not exist, the column will be created and the cell content is set to the argument value.

<b>Method</b>	<b>Description</b>	<b>Arguments</b>	<b>Notes about function behavior</b>
LR.vtcAddCells (colNames, values,option, VtsName)	<p>Sets the data in multiple columns.</p> <p>If option selected is 2, returns a value of 0 if value inserted.</p> <p>Returns a value of 1 if the value already exists.</p>	<p><b>ColNames.</b>The column names delimited by a semi-colon.</p> <p><b>values.</b>The values as a string delimited by a semi-colon.</p> <p><b>option..</b>Define how the values are added</p> <p><b>0.</b> Add as same row in all columns based on the column with the highest row count. The created row will be n+1 for all columns.</p> <p><b>1.</b> Add as stack - last row in every column.</p> <p><b>2.</b> Add as unique stack - last row in every column only if the value is unique in the column.</p> <p><b>VtsName.</b>The alias of the VTS server.</p>	<p>If the columns specified in the argument do not exist, the columns will be created and the cell contents are set to the argument values.</p>

Method	Description	Arguments	Notes about function behavior
LR.vtcAddUniqueCell (colName, value, VtsName)	<p>Sets the last field of a column to a value if the value does not exist in the column.</p> <p>Returns a value of 0 if a value is inserted.</p> <p>Returns a value of 1 if the value already exists.</p>	<p><b>ColName.</b> The name of the column.</p> <p><b>value.</b> The value.</p> <p><b>VtsName.</b> The alias of the VTS server.</p>	If the column specified in the argument does not exist, the column will be created and the cell content is set to the argument value.
LR.vtcClearColumn (colName,VtsName)	Clears all data in a column.	<p><b>colName.</b> The name of the column.</p> <p><b>VtsName.</b> The alias of the VTS server.</p>	If the column specified in the argument does not exist, the step will run without returning an error and no data in the VTS is changed.
LR.vtcClearCell (colName,rowIndex,VtsName)	Clears the data in a field.	<p><b>colName.</b> The name of the column.</p> <p><b>rowIndex.</b> The index number of the field as an integer. 1 is the first field in the column.</p> <p><b>VtsName.</b> The alias of the VTS server.</p>	If the column or the row index specified in the argument does not exist, the step will run without returning an error and no data in the VTS will be changed.

<b>Method</b>	<b>Description</b>	<b>Arguments</b>	<b>Notes about function behavior</b>
LR.vtcColumnSize (colName, VtsName)	Returns the number of fields that contain data in a column.	<b>colName.</b> The name of the column.  <b>VtsName.</b> The alias of the VTS server.	If the column specified in the argument does not exist, the step will run without returning an error and the return value is 0.
LR.vtcConnect (serverName, port, VtsName)	Creates a connection to the server.	<b>serverName.</b> Either the IP or server name.  <b>port.</b> The port number  <b>VtsName..</b> The alias of the VTS server.	
LR.vtcDisconnect (VtsName)	Disconnects from the server.	<b>VtsName.</b> The alias of the VTS server.	
LR.vtcDropIndex (colName,VtsName)	Deletes the index on a column.	<b>colName.</b> The column name.  <b>VtsName.</b> The alias of the VTS server.	If the column specified in the argument does not exist, the step will run without returning an error.  In addition, if the index has already been dropped on the column, the step will run without returning an error.
LR.vtcEnsureIndex (colName,VtsName)	Creates an index on a column.	<b>colName.</b> The name of the column.  <b>VtsName.</b> The alias of the VTS server.	If the column specified in the argument does not exist, the step will run without returning an error.  In addition, if the index has already been created on the column, the step will run without returning an error.

Method	Description	Arguments	Notes about function behavior
LR.vtcIncrement (colName, rowIndex, value , VtsName)	Increments a counter stored in a field.	<b>colName.</b> The name of the column.  <b>rowIndex.</b> The index number of the field as an integer. 1 is the first field in the column.  <b>value.</b> The value as a string.  <b>VtsName.</b> The alias of the VTS server.	If the column name specified in the argument does not exist, the column will be created and the cell referenced by the index will be set to the argument value.  If the index specified in the argument exceeds the column size, the cell is created by the specified index and the cell contents is set to the argument value.  If the column referenced by the index contains a string, the cell contents are replaced with the value argument.
LR.vtcGetRowCell (colName, rowIndex, VtsName)	Returns the data in a field.	<b>colName.</b> The name of the column.  <b>rowIndex.</b> The index number of the field as an integer. 1 is the first field in the column.  <b>VtsName.</b> The alias of the VTS server.	If the column name or index name specified in the argument does not exist, a null value will be returned.
LR.vtcGetRowCells (rowIndex, VtsName)	Returns the data in a row as a javascript object. The properties of the object will be set to the column names.	<b>rowIndex.</b> The index number of the field . 1 is the first field in the column.  <b>VtsName..</b> The alias of the VTS server.	If the column specified in the argument does not exist, a null value will be returned for every column.

Method	Description	Arguments	Notes about function behavior
LR.vtcPopCell (colName,VtsName)	Pops the first field from a column.	<b>colName.</b> The name of the column.  <b>VtsName.</b> The alias of the VTS server.	If the column name specified in the argument does not exist, a null value will be returned.
LR.vtcPopMultipleCells (colNames,VtsName)	Pops the first fields from specified columns. Returned as a javascript object. The properties of the object will be set to the column names.	<b>colNames.</b> The names of the columns.  <b>VtsName.</b> The alias of the VTS server.	If the column names specified in the argument does not exist, a null value will be returned.
LR.vtcUpdateCell (colName,rowIndex,value ,VtsName)	Replaces the data in a field.	<b>colName.</b> The name of the column.  <b>rowIndex.</b> The index number of the field as an integer. 1 is the first field in the column.  <b>value.</b> The value as a string.  <b>VtsName.</b> The alias of the VTS server.	If the column name or index does not exist, the column and/ or the cell referenced by the index will be created and the cell contents set to the argument value.

<b>Method</b>	<b>Description</b>	<b>Arguments</b>	<b>Notes about function behavior</b>
LR.vtcUpdateEqualsCell (colName, rowIndex, value, comparedValue, VtsName)	<p>Replaces the data in a field if the current data equals a given value.</p> <p>Returns a value of 0 if the value is updated.</p> <p>Returns a value of 1 if the value does not match the compare value.</p>	<b>colName.</b> The name of the column.  <b>rowIndex.</b> The index number of the field as an integer. 1 is the first field in the column.  <b>value.</b> The value as a string.  <b>comparedValue.</b>  <b>VtsName.</b> The alias of the VTS server.	If the column name or index does not exist, the column and/ or the cell pointed to by the row index will be created and the cell contents set to the argument value.
LR.vtcUpdateRowCells (colNames, rowIndex, values, VtsName)	Replaces the data in a row.	<b>colNames.</b> The name of the columns.  <b>rowIndex.</b> The index number of the field as an integer. 1 is the first field in the column.  <b>values.</b> The values as a string delimited by semi-colons.  <b>VtsName.</b> The alias of the VTS server.	If the column names or index does not exist, the columns and/ or the cells referenced by the index will be created and the cells contents are set to the argument values.

## TruClient Properties

These properties can be used as arguments in TruClient functions.

Property	Description
LR.userId	The user ID as it appears in the MDRV command line. MDRV is the main process that runs all protocols.
LR.groupName	The group name as it appears in the MDRV command line. MDRV is the main process that runs all protocols. If the process was started by VuGen its value is 0.
LR.scenarioid	The scenario ID as it appears in the MDRV command line. MDRV is the main process that runs all protocols. The scenario ID exists only if MDRV was started by Controller, if it was started by VuGen its value is 0.
LR.outputDir	The user output folder that contains all the output for the script. For VuGen the output folder and script folder are the same. For Controller they are different. The returned path includes the last folder separator.
LR.scriptDir	The user script folder. You can store external files in the script folder such that when you want to include them in your script, you can append the filename of your external file to LR.scriptDir.

## TruClient Step Arguments

The following table displays the step arguments categorized by role. Mandatory arguments are marked with a red star to the left of the argument name in the user interface. All arguments can accept JavaScript code and LoadRunner functions as values. For a list of LoadRunner functions, see [TruClient Functions](#).

Role	Action	Arguments
element	Evaluate JavaScript	Code: JavaScript code

Role	Action	Arguments
element	Mouse Actions: Mouse Down, Mouse Up, Mouse Over, Click, Double Click	<ul style="list-style-type: none"> <li>• <b>Button.</b> The mouse button that is clicked.</li> <li>• <b>X Coordinate.</b> The offset location of the action relative to the upper left corner of the object. This number must be positive. If not specified, the default is the center of the object.</li> <li>• <b>Y Coordinate.</b> The offset location of the action relative to the upper left corner of the object. If not specified, the default is the center of the object.</li> <li>• <b>Ctrl Key.</b> Whether or not this key is pressed during the action.</li> <li>• <b>Alt Key.</b> Whether or not this key is pressed during the action.</li> <li>• <b>Shift Key.</b> Whether or not this key is pressed during the action.</li> </ul>
element	Drag	<ul style="list-style-type: none"> <li>• <b>Button.</b> The mouse button that is clicked.</li> <li>• <b>X Offset.</b> The amount of pixels to drag the object on the x axis. A positive number indicates a drag to the right.</li> <li>• <b>Y Offset.</b> The amount of pixels to drag the object on the y axis. A positive number indicates a drag down.</li> <li>• <b>Path.</b> List of coordinates representing user drag path. Do not modify this argument.</li> </ul>
element	Drag To	<ul style="list-style-type: none"> <li>• <b>Target Object.</b> The step object is dragged to this target object.</li> <li>• <b>X Offset.</b> The offset from the top left of the target object in the x axis. This number must be positive.</li> <li>• <b>Y Offset.</b> The offset from the top left of the target object in the y axis. This number must be positive.</li> </ul>

Role	Action	Arguments
element	Get Property	<ul style="list-style-type: none"> <li>• <b>Property.</b> The property whose value will be stored in the specified variable. The list of properties available depends on all the roles of the object.</li> </ul> <p>The following are the default properties available for all objects:</p> <ul style="list-style-type: none"> <li>▪ <b>Visible text.</b> The visible text of the item, corresponding to the DOM textContent property.</li> <li>▪ <b>All text.</b> The entire text of the item, corresponding to the DOM textContent property.</li> <li>▪ <b>Inner HTML.</b> The inner html markup of the object, corresponding to the DOM innerHTML property.</li> <li>▪ <b>Variable.</b> The name of the variable in which to store the specified property value.</li> </ul>
element	Verify	<ul style="list-style-type: none"> <li>• <b>Value.</b> The string or number to verify.</li> <li>• <b>Property.</b> The object property whose value will be verified. The list of properties available to verify depends on all the roles of the object.</li> </ul> <p>The following are the default properties available for verification on all objects:</p> <ul style="list-style-type: none"> <li>▪ <b>Visible text.</b> Items that are visible in the application.</li> <li>▪ <b>All text.</b> Items that are in the application but are not necessarily visible. Items in this category are contained in DOM property textContent.</li> <li>▪ <b>Inner HTML.</b> Items contained in the DOM property innerHTML.</li> <li>▪ <b>Condition.</b> The relationship between the value and property arguments.</li> </ul>

Role	Action	Arguments
element	Wait for Property	<ul style="list-style-type: none"> <li><b>Value.</b> The value of the specified property that the step will wait for, before the step passes.</li> <li><b>Property.</b> The object property whose value the script will wait for. The list of properties available for which to wait, depends on all the roles of the object.</li> </ul> <p>The following are the default properties available for all objects:</p> <ul style="list-style-type: none"> <li><b>Visible text.</b> Items that are visible in the application.</li> <li><b>All text.</b> Items that are in the application but are not necessarily visible. Items in this category are contained in DOM property textContent.</li> <li><b>Inner HTML.</b> Items contained in the DOM property innerHTML.</li> <li><b>Condition.</b> The relationship between the value and property arguments.</li> </ul>
focusable	Press Key	<ul style="list-style-type: none"> <li><b>Key name.</b> Enter or Space.</li> </ul>
text box	Type	<ul style="list-style-type: none"> <li><b>Value.</b> What is typed.</li> <li><b>Clear.</b> Clear the text box before typing. The default is true.</li> <li><b>Typing Interval.</b> The average time in milliseconds between keystrokes.</li> </ul>
check box	Set	<ul style="list-style-type: none"> <li><b>Checked.</b> Set the check box to either checked (T) or unchecked (F).</li> </ul>
listbox	Select	<ul style="list-style-type: none"> <li><b>Text.</b> The selected string.</li> <li><b>Ordinal.</b> The order of the selected item in the list. If the text argument is also specified, than this argument refers to the instance of the specified text value in the listbox. An ordinal of 0 generates a random value.</li> </ul>
radiogroup	Select	<ul style="list-style-type: none"> <li><b>Text.</b> The selected string.</li> <li><b>Ordinal.</b> The order of the selected item in the list. If the text argument is also specified, than this argument refers to the instance of the specified text value in the listbox. An ordinal of 0 generates a random value.</li> </ul>
filebox	Set	<ul style="list-style-type: none"> <li><b>Path.</b> The selected path.</li> </ul>

Role	Action	Arguments
slider	Set	<ul style="list-style-type: none"> <li><b>Value.</b> The value that the slider is set to.</li> </ul>
datepicker	Set Day	<ul style="list-style-type: none"> <li><b>Day.</b> An integer between 1-31 representing the day of the month.</li> </ul>
browser	Activate	<ul style="list-style-type: none"> <li><b>Ordinal.</b> Defined as an integer. Moves the specified browser window to the foreground.</li> </ul>
browser	Activate Tab	<ul style="list-style-type: none"> <li><b>Ordinal.</b> Which tab (integer) to activate.</li> </ul>
browser	Close Tab	<ul style="list-style-type: none"> <li><b>Ordinal.</b> Which tab (integer) to close.</li> </ul>
browser	Add Tab	<ul style="list-style-type: none"> <li><b>Location.</b> The URL to navigate to in the newly opened tab.</li> </ul>
browser	Navigate	<ul style="list-style-type: none"> <li><b>Location.</b> The URL to navigate to.</li> </ul>
browser	Go Back	<ul style="list-style-type: none"> <li><b>Count.</b> The number of pages to go back.</li> </ul>
browser	Go Forward	<ul style="list-style-type: none"> <li><b>Count.</b> The number of pages to go forward.</li> </ul>
browser	Resize	<ul style="list-style-type: none"> <li><b>Width.</b> The new width. Leaving this blank means do not resize the width.</li> <li><b>Height.</b> The new height. Leaving this blank means do not resize the height.</li> </ul>
browser	Scroll	<ul style="list-style-type: none"> <li><b>X Coordinate.</b> The new x coordinate. Leaving this blank means do not scroll along the x axis.</li> <li><b>Y Coordinate.</b> The new y coordinate. Leaving this blank means do not scroll along the y axis.</li> </ul>
browser	Dialog - Confirm	<ul style="list-style-type: none"> <li><b>Button.</b> Ok or Cancel.</li> </ul>
browser	Dialog Prompt	<ul style="list-style-type: none"> <li><b>Value.</b> The string to enter.</li> <li><b>Button.</b> Ok or Cancel.</li> </ul>
browser	Dialog - Authentication	<ul style="list-style-type: none"> <li><b>Username.</b> The username to enter.</li> <li><b>Password.</b> The password to enter.</li> <li><b>Domain.</b> The domain to enter.</li> <li><b>Button.</b> Ok or Cancel.</li> </ul>

Role	Action	Arguments
browser	Verify	<ul style="list-style-type: none"> <li><b>Value.</b> The value of the property to verify.</li> <li><b>Property.</b> The property to verify. You can verify the following properties of a browser object:</li> <li><b>Title.</b> The title of the browser window.</li> <li><b>Location.</b> The location of the browser window.</li> <li><b>Condition.</b> The relationship between the value and property arguments.</li> </ul>

## Citrix Protocol

### Citrix Protocol - Overview

Citrix Vuser scripts emulate Citrix ICA protocol communication between a Citrix client and server. VuGen records all activity during the communication and creates a Vuser script.

When you perform actions on the remote server, VuGen generates functions that describe these actions. Each function begins with a **ctrx** prefix. These functions emulate the analog movements of the mouse and keyboard. In addition, the **ctrx** functions allow you to synchronize the replay of the actions, by waiting for specific windows to open.

VuGen also allows you to record a Citrix NFUSE session. With Citrix NFUSE, the client is installed, but your interface is a browser instead of a client interface. To record NFUSE sessions, you must perform a multi-protocol recording for Citrix and Web Vusers. In multi-protocol mode, VuGen generates functions from both Citrix and Web protocols during recording.

In the following example, **ctrx\_mouse\_click** simulates a mouse click on the left button.

```
ctrx_mouse_click(44, 318, LEFT_BUTTON, 0, CTRX_LAST);
```

For more information about the syntax and parameters, see the Function Reference ([Help > Function Reference](#)).

## Citrix Recording Tips

When recording a Citrix Vuser script, be sure to follow these guidelines in order to create an effective script.

### Single vs. Multi-Protocol Scripts

When creating a new script, you may create a single protocol or multi-protocol script. If you plan to record a simple Citrix ICA session, use a single protocol script. When recording an NFUSE Web Access session, however, you must create a multi-protocol script for Citrix ICA and Web (HTML/HTTP), to enable the recording of both protocols.

## Record into Appropriate Sections

Record the connection process into the **vuser\_init** section, and the closing process into the **vuser\_end** section. This will prevent you from performing iterations on the connecting and disconnecting. For more information about recording into sections, see "["Vuser Script Sections" on page 255](#)".

## Run a Clean Session

When recording a session, make sure to perform the complete business process, starting with the connection and ending with the cleanup. End your session at a point from where you could start the entire process from the beginning. Do not leave any client or application windows open.

## Explicit Clicks

When opening expanded menu options, click explicitly on each option—do not depend on the expanding menu. For example, when choosing **Start > All Programs > Microsoft Word**, be sure to click on the line **All Programs**.

## Do not Resize Windows

Although VuGen supports the resizing of windows during recording the session, we recommend that you do not move or resize them while recording. To change the size or position of a window, double-click on the relevant **Sync on Window** step in the **Step Navigator** and modify the window's coordinates.

## Make Sure Resolution Settings are Consistent

To insure successful bitmap synchronization, make sure that the resolution settings match. On the recording machine, check the settings of the ICA client, the Recording Options, and the Run Time settings. On the load generators, check the settings of the ICA client, and make sure that they are consistent between all load generators and recording machines. If there is an inconsistency between the resolutions, the server traffic increases in order to make the necessary adjustments.

## Add Manual Synchronization Points

While waiting for an event during recording, such as the opening of an application, we recommend that you add manual synchronization points, such as **Sync on Bitmap** or **Sync on Text**. For details, see "["Citrix - Automatic Synchronization" on page 587](#)".

## Disable Client Updates

Disable client updates when prompted by the Citrix client. This will prevent forward compatibility issues between VuGen and newer Citrix clients that were not yet tested.

## Windows Style

For **Sync on Bitmap** steps, record windows in the "classic" windows style—not the XP style.

## Change the Windows Style to "classic"

1. Click in the desktop area.
2. Select **Properties** from the right-click menu.
3. Click the Theme tab.

4. From the **Theme** list, select **Windows Classic**.

5. Click **OK**.

## Citrix Replaying Tips

### Wildcards

You can use wildcards (\*) in defining window names. This is especially useful where the window name may change during replay, by its suffix or prefix.

In the following example, the title of the **Microsoft Internet Explorer** window was modified with a wildcard.

```
ctrx_mouse_click(573, 61, LEFT_BUTTON, 0,  
"Welcome to MSN.com - Microsoft Internet Explorer");ctrx_mouse_click(573, 61, LE  
FT_BUTTON, 0,  
"* - Microsoft Internet Explorer");
```

For more information, see the Function Reference ([Help > Function Reference](#)).

### Set Initialization Quota

To prevent overloading by multiple Vusers while connecting, set an initialization quota of 4 to 10 Vusers (depending on the capacity of the server) or apply ramp-up initialization using the Scheduler.

### Enable Think Time

For best results, do not disable think time in the run-time settings. Think time is especially relevant before the **ctrx\_sync\_on\_window** and **ctrx\_sync\_on\_bitmap** functions, which require time to stabilize.

### Regenerate Script

During recording, VuGen saves all of the agent information together with the script. By default, it also includes this information in the script, excluding the **Sync On Text** steps. If you encounter text synchronization issues, then you can regenerate the script to include the text synchronization steps.

In addition, if you disabled the generation of agent information in the Recording options, you can regenerate the script to include them.

Regenerating scripts is also useful for scripts that you manually modified. When you regenerate the script, VuGen discards all of your manual changes and reverts back to the originally recorded version.

To regenerate a script, select **Record > Regenerate Script** and select the desired options. For more information about regenerating scripts, see "[How to Regenerate a Vuser Script](#)" on page 266.

### Set Consistency Between Machines

If you intend to replay the script on another machine, make sure that the following items are consistent between the record and replay machines: Window Size (resolution), Window Colors, System Font and the other Default Options settings for the Citrix client. These settings affect the hash value of bitmaps, and inconsistencies may cause replay to fail. To view the Citrix Client

settings, select an item from the Citrix program group and select **Application Set Settings** or **Custom Connection Settings** from the right-click menu. Select the Default Options tab.

## Increasing the Number of Vusers per Load Generator Machine

Load Generator machines running Citrix Vusers may be limited in the number of Vusers that can run, due to the graphic resources available to that machine, also known as the GDI (Graphics Device Interface). To increase the number of Vusers per machine, you can open a terminal server session on the machine which acts as an additional load generator.

The GDI count is Operating System dependent. The actual GDI (Graphics Device Interface) count for a heavily loaded machine using LoadRunner is approximately 7,500. The maximum available GDI on Windows 2000 machines is 16,384.

For more information on creating a terminal server session, see "[Terminal Services Overview](#)" on [page 1146](#).

**Note:** By default, sessions on a terminal server use a 256-color set. If you intend to use a terminal session for load testing, make sure to record on machines with a 256-color set.

## Citrix Synchronization

Synchronization refers to waiting for windows and objects to become available before executing an action. This is necessary when recording Citrix scripts because, for example, if a step in a script opens a window, and the next step performs an action in that window, the second step cannot be implemented until the window opens. In order to ensure that VuGen does not replay the script incorrectly, it automatically generates functions that synchronize the script by waiting for windows or objects to become available. In addition, you can add synchronization functions manually.

For information about automatic synchronization, see "[Citrix - Automatic Synchronization](#)" below.

For information about manually adding synchronization points, see "[How to Synchronize Citrix Scripts Manually](#)" on [page 594](#).

## Citrix - Automatic Synchronization

During recording, VuGen automatically generates steps that help synchronize the Vuser's replay of the script:

### Sync on Window

The **Sync On Window** step instructs the Vuser to wait for a specific event before resuming replay. The available events are **Create** and **Active**. The Create event waits until the window is created. The Active event waits until the window is created and then activated (in focus). Usually VuGen generates a function with a create event. If, however, the next instruction is a keyboard event, VuGen generates a function with an active event.

In the Editor, the corresponding function call to the **Sync On Window** step is `ctrx_sync_on_window`.

## Sync on Obj Info

The **Sync On Obj Info** step instructs the Vuser to wait for a specific object property before resuming replay. The available attributes are **Enabled**, **Visible**, **Focused**, **Text**, **Checked**, **Lines**, or **Item**. The Enabled, Visible, Focused, and Checked attributes are boolean values that can receive the values **true** or **false**. The other attributes require a textual or numerical object value.

A primary objective of this step is to wait for an object to be in focus before performing an action upon it.

VuGen automatically generates **sync\_on\_obj\_info** steps when the Citrix agent is installed and the Use Citrix Agent Input in Code Generation option is enabled in the Recording options. By default, this Recording option is enabled. For more information, see "[Citrix > Code Generation](#)" on page [177](#).

```
ctrx_sync_on_obj_info("Run=snapshot9", 120, 144, TEXT, "OK",
                      CTRX_LAST);
```

## Sync on Text

The Text Synchronization step, **Sync On Text**, instructs the Vuser to wait for a text string to appear at the specified position before continuing. When replaying **Sync On Text**, Vusers search for the text in the rectangle whose modifiable coordinates are specified in the step's properties.

**Caution:** The maximum allowable length of a text string is 255 characters.

With an agent installation (see "[Agent for Citrix Presentation Server - Overview](#)" on page [590](#)), you can instruct VuGen to automatically generate a text synchronization step before each mouse click or double-click. By default, automatic text synchronization is disabled. For more information, see "[Citrix > Code Generation](#)" on page [177](#).

Note, that even if you record a script with the option disabled, if you enable the option and regenerate the script, VuGen will insert text synchronization calls throughout the entire script.

In the Editor, the corresponding function call to the **Sync On Text** step is **ctrx\_sync\_on\_text\_ex**.

The following segment shows a **ctrx\_sync\_on\_text\_ex** function that was recorded during a Citrix recording with the HP Citrix Agent installed and text synchronization enabled.

```
ctrx_sync_on_window ("ICA Seamless Host Agent", ACTIVATE, 0, 0,391,224, "snapshot1", CTRX_LAST);
ctrx_sync_on_text_ex (196, 198, 44, 14, "OK", "ICA Seamless Host Agent=snapshot2", CTRX_LAST);
ctrx_obj_mouse_click ("<class=Button text=OK>", 196, 198, LEFT_BUTTON, 0, "ICA Seamless Host Agent=snapshot2", CTRX_LAST);
```

For more information on this function, see the Function Reference ([Help > Function Reference](#)).

See "[Citrix Alternate Synchronization](#)" below for additional information.

## Citrix Alternate Synchronization

In addition to [automatic synchronization](#) in Citrix Vuser scripts, you can add several other steps that affect the synchronization indirectly:

## Setting the Waiting Time

The **Set Waiting Time** step sets a waiting time for the other Citrix synchronization functions. This setting applies to all functions that follow it within the script. For example, if your **Sync on Window** steps are timing out, you can increase the default timeout from 60 seconds to 180 seconds.

To insert this step, select **Insert > Add Step > Set Waiting Time**.

## Checking if a Window Exists or Closed

The **ctrx\_win\_exist** step checks if a window is visible in the Citrix client. By adding control flow statements, you can use this function to check for a window that does not always open, such as a warning dialog box. In the following example, **ctrx\_win\_exist** checks whether a browser was launched. The second argument indicates how long to wait for the browser window to open. If it did not open in the specified time, it double-clicks its icon.

```
if (!ctrx_win_exist("Welcome", 6, CTRX_LAST))
    ctrx_mouse_double_click(34, 325, LEFT_BUTTON, 0, CTRX_LAST)
```

To insert this step, select **Insert > Add Step > Win Exist**.

Another useful application for this step is to check if a window has been closed. If you need to wait for a window to close, you should use a synchronization step such as **UnSet Window** or **ctrx\_unset\_window**.

For detailed information about these functions, see the Function Reference (**Help > Function Reference**).

## Waiting for a Bitmap Change

In certain cases, you do not know what data or image will be displayed in an area, but you do expect it to change. To emulate this, you can use the **Sync on Bitmap Change** step or its corresponding function, **ctrx\_sync\_on\_bitmap\_change**. Right-click in the snapshot, and select **Insert Sync on Bitmap** from the right-click menu. VuGen inserts the step or function at the location of the cursor.

The syntax of the functions is as follows:

```
ctrx_sync_on_bitmap (x_start, y_start, width, height, hash, CTRX_LAST);
ctrx_sync_on_bitmap_change (x_start, y_start, width, height,
                           [initial_wait_time,] [timeout,]
                           [initial_bitmap_value,] CTRX_LAST);
```

The following optional arguments are available for **ctrx\_sync\_on\_bitmap\_change**:

- initial wait time value—when to begin checking for a change.
- a timeout—the amount of time in seconds to wait for a change to occur before failing.
- initial bitmap value—the initial hash value of the bitmap. Vusers wait until the hash value is different from the specified initial bitmap value.

In the following example, the recorded function was modified and assigned an initial waiting time of 300 seconds and a timeout of 400 seconds.

```
ctrx_sync_on_bitmap_change(93, 227, 78, 52,
                           300,400, "66de3122a58baade89e63698d1c0d5dfa", CTRX_LAST);

```

**Note:** If you are using **Sync on Bitmap**, make sure that the Configuration settings in the Controller, Load Generator machine, and screen are the same. Otherwise, VuGen may be unable to find the correct bitmaps during replay. For information on how to configure the client settings, see ["Recording Options" on page 176](#).

## Agent for Citrix Presentation Server - Overview

The Agent for Citrix Presentation Server, or Citrix Agent, is an optional utility that you can install on the Citrix server. It provides enhancements to the normal Citrix functionality. The following sections describe these enhancements.

It is provided in the product's installation disk and you can install it on any Citrix server. For more information about installing the Citrix Agent, see ["How to Install and Uninstall the Citrix Agent" on page 595](#).

### Object Detail Recording

When the Agent for Citrix Presentation Server is installed, VuGen records specific information about the active object instead of general information about the action. For example, VuGen generates **Obj Mouse Click** and **Obj Mouse Double Click** steps instead of **Mouse Click** and **Mouse Double Click** that it generates without the agent.

The following example shows the same mouse-click action recorded with and without the agent installation. Note that with an agent, VuGen generates `ctrx_obj_xxx` functions for all of the mouse actions, such as click, double-click and release.

```
/* Without Agent Installation */
ctrx_mouse_click(573, 61, LEFT_BUTTON, 0, test3.txt - Notepad);
/* With Agent Installation */
ctrx_obj_mouse_click("<text=test3.txt - Notepad class=Notepad>" 573,
                     61, LEFT_BUTTON, 0, test3.txt - Notepad=snapshot21, CTRX_LAST);
```


In the example above, the first argument of the `ctrx_obj_mouse_click` function contains the text of the window's title and the class, Notepad. Note that although the agent provides additional information about each object, Vusers only access objects by their window name and its coordinates.

### Active Object Recognition

The agent installation lets you see which objects in the client window are detected by VuGen. This includes all Windows Basic Objects such as edit boxes, buttons, and item lists in the current window.

To see which objects were detected, you move your mouse through the snapshot. VuGen highlights the borders of the detected objects as the mouse passes over them.

In the following example, the **Yes** button is one of the detected objects.



## Expanded Right-Click Menu

When you click within a snapshot, you can insert several functions into the script using the right-click menu. When no agent is installed, you are limited to the **Insert Mouse Click**, **Insert Mouse Double Click**, **Insert Sync on Bitmap** and **Insert Get Bitmap Value**. If you are using a 256-color set, the **Insert Sync on Bitmap** and **Get Bitmap Value** steps are not available from the right-click menu.

When the Agent for Citrix Presentation Server is installed, the following additional options are available from the right-click menu of window in focus:

- **Obj Get Info** and **Sync on Obj Info**. Provide information about the state of the object: ENABLED, FOCUSED, VISIBLE, TEXT, CHECKED, and LINES.
- **Insert Sync on Obj Info**. Instructs VuGen to wait for a certain state before continuing. This is generated as a `ctrx_sync_on_obj_info` function.
- **Insert Obj Get Info**. Retrieves the current state of any object property. This is generated as a `ctrx_get_obj_info` function.
- **Insert Sync on Text and Get Text**. These are discussed in the section [Agent for Citrix Presentation Server - Overview](#).

These commands are interactive—when you insert them into the script, you mark the object or text area in the snapshot.

In the following example, the `ctrx_sync_on_obj_info` function provides synchronization by waiting for the Font dialog box to come into focus.

```
ctrx_sync_on_obj_info("Font", 31, 59, FOCUSED, "TRUE", CTRX_LAST);
```

Utilizing VuGen's ability to detect objects, you can perform actions on specific objects interactively, from within the snapshot.

## Insert a Function Interactively Using the Agent Capabilities


1. Click at a point within the Step Navigator to insert the new step. Make sure that a snapshot is visible.
2. Click within the snapshot.
3. To mark a bitmap, right-click on it and select **Insert Sync on Bitmap**.

VuGen issues a message indicating that you need to mark the desired area by dragging the cursor. Click **OK** and drag the cursor diagonally across the bitmap that you want to select.

When you release the mouse, VuGen inserts the step into the script after the currently selected step.

4. For all other steps, move your mouse over snapshot objects to determine which items are active—VuGen highlights the borders of active objects as the mouse passes over them.

Right-click and select one of the Insert commands. A dialog box opens with the step's properties.



Set the desired properties and click **OK**. VuGen inserts the step into your script.

## Text Retrieval

With the agent installed, VuGen lets you save standard text to a buffer. Note that VuGen can only save true text—not a graphical representation of text in the form of an image.

You save the text using the **Sync On Text** step either during or after recording.

For task details, see "[How to Synchronize Citrix Scripts Manually](#)" on the next page.

## Troubleshooting XenApp 5.0

When recording with XenApp 5.0 using a Citrix and Web multi-protocol script, manual modifications are needed to ensure proper recording.

### Record using XenApp 5.0

#### 1. Modify XenApp Settings:

- a. Connect to the XenApp server through a web interface.
- b. Select **Preferences > Session Settings** and set **Window Size** to **No Preference**.

#### 2. Update Correlation Rules

#### 3. Modify Recording Options

- a. Open the **General > Recording** node of the Recording Options dialog box.
- b. Select **Advanced HTML** to open the Advanced HTML dialog box.
- c. Select **A script containing explicit URL's only**.

#### 4. Manually Modify Script

## How to Configure the Citrix Client and Server

Before creating a script, make sure you have a supported Citrix client installed on your machine, and that your server is properly configured.

### Configure the Citrix client

In order to run your script, you must install a Citrix client on each Load Generator machine. If you do not have a client installed, you can download one from the Citrix website [www.citrix.com](http://www.citrix.com) under the **download** section.

VuGen supports all Citrix clients with the exception of versions 8.00, version 6.30.1060 and earlier, and Citrix Web clients.

### Install the MetaFrame server

Make sure the MetaFrame server (3, 4, or 4.5) is installed. To check the version of the server, select **Citrix Connection Configuration** on the server's console toolbar and select **Help > About**.

### Configure the MetaFrame server

Configure the Citrix server to completely close a session. After a Citrix client closes the connection, the server is configured, by default, to save the session for the next time that client opens a new connection. Consequently, a new connection by the same client will face the same workspace from which it disconnected previously. It is preferable to allow each new test run to use

a clean workspace.

The make sure that you have a clean workspace for each test, you must configure the Citrix server not to save the previous session. Instead, it should reset the connection by disconnecting from the client each time the client times-out or breaks the connection.

## Configure the server

1. Open the Citrix Connection Configuration dialog box. Select **All Programs > Citrix > Administration Tools > Citrix Connection Configuration Tool**.
2. Select the ica-tcp connection name and select **Connection > Edit**. Alternatively, double-click on the connection. The Edit Connection dialog box opens.
3. Click **Advanced**. The Advanced Connection Settings dialog box opens.
4. In the bottom section of the dialog box, clear the **inherit user config** check box adjacent to the **On a broken or timed-out connection** list. Change the entry for this list box to **reset**.

# How to Synchronize Citrix Scripts Manually

In addition to the automatic synchronization, you can manually add synchronization both during and after recording. A common use of this capability is where the actual window did not change, but an object within the window changed. Since the window did not change, VuGen did not detect or record a **Sync on Window**.

For example, if you want the replay to wait for a specific graphic image in a browser window, you insert manual synchronization. Or, if you are recording a large window with several tabs, you can insert a synchronization step to wait for the new tab's content to open.

## Synchronize manually during recording

To add synchronization during recording, you use the floating toolbar. The **Sync On Bitmap** and **Sync on Text** functions lets you to mark an area or text within the client window that needs to be in focus before resuming replay.

- To insert a **Sync on Bitmap** step, click the **InsertSync on Bitmap**  button on the toolbar and mark a rectangle around the desired area.
- To insert a **Sync on Text** step (Citrix Agent required), click the **Insert Sync On Text**  button on the toolbar and mark a rectangle around the desired text.

## Synchronize manually after recording

You can also add synchronization after the recording session. To add a synchronization step, right-click in the Snapshot pane, and select a synchronization option:

- **Sync on Bitmap**. Waits until a bitmap appears
- **Sync on Obj Info**. Waits until an object's attributes have the specified values (agent

installations only)

- **Sync on Text.** Waits until the specified text is displayed (agent installations only)

## How to Install and Uninstall the Citrix Agent

The installation file for the Agent for Citrix Presentation Server is located on the LoadRunner installation disk, under the **Additional Components\ Agent for Citrix Presentation Server** folder.

Note that the agent should be installed on your Citrix server machine only—not on Load Generator machines.

### Install the Agent for Citrix Presentation Server

1. If you are upgrading the agent, make sure to uninstall the previous version before installing the next one.
2. If your server requires administrator permissions to install software, log in as an administrator to the server.
3. Locate the installation file, **SetupCitrixAgent<arch>.exe**, on the product installation disk in the **Additional Components\ Agent for Citrix Presentation Server\Win32 or Win64** folder.
4. Follow the installation wizard to completion.

**Note:** After installation the agent will only be active for LoadRunner invoked Citrix sessions—it will not be active for users who start a Citrix session without LoadRunner.

### Uninstall the Agent for Citrix Presentation Server

1. If your server requires administrator privileges to remove software, log in as an administrator to the server.
2. Open **Add/Remove Programs** in the server machine's Control Panel. Select **HP Software Agent for Citrix Presentation Server 32 or 64** and click **Change/Remove**.

## Citrix Functions

During a Citrix recording session, VuGen generates functions that emulate the communication between a client and a remote server. The generated functions have a **ctrx** prefix. For example, **ctrx\_obj\_mouse\_click** emulates a mouse click for a specific object. You can manually edit or add any of the functions into your Vuser script after the recording session.

For more information about the **ctrx** functions, see the Function Reference (**Help > Function Reference**).

Note that for the functions that specify a window name, you can use the wildcard symbol, an asterisk (\*). You can place the wildcard at the beginning, middle, or end of the string.

## Citrix - Understanding ICA Files

Citrix ICA client files are text files that contain configuration information for the applications accessed through the Citrix client. These files must have an .ica extension and must conform to the following format:

```
[WFClient]
Version=
TcpBrowserAddress=

[ApplicationServers]
AppName1=

[AppName1]
Address=
InitialProgram=# 
ClientAudio=
AudioBandwidthLimit=
Compress=
DesiredHRES=
DesiredVRES=
DesiredColor=
TransportDriver=
WinStationDriver=
Username=
Domain=
ClearPassword=
```

**Note:** When you load an ICA file using the Recording Options, VuGen saves the file together with your script, eliminating the need to copy the ICA file to each load generator machine.

The following example shows a sample ICA file for using Microsoft Word on a remote machine through the Citrix client:

```
[WFClient]
Version=2
TcpBrowserAddress=235.119.93.56

[ApplicationServers]
Word=

[Word]
Address=Word
InitialProgram=#Word
ClientAudio=On
```

```

AudioBandwidthLimit=2
Compress=On
DesiredHRES=800
DesiredVRES=600
DesiredColor=2
TransportDriver=TCP/IP
WinStationDriver=ICA 3.0
Username=test
Domain=user_lab
ClearPassword=test

```

For more information, see the Citrix website [www.citrix.com](http://www.citrix.com).

## Failed Bitmap Synchronization Dialog Box

This dialog box enables you to decide what to do when a bitmap synchronization fails.

<b>To access</b>	This dialog box opens automatically during replay when there is a mismatch between the record snapshot and the replay snapshot in a bitmap synchronization step.
------------------	--

User interface elements are described below:

UI Element	Description
<b>Continue</b>	Accept the mismatch and use both the original and new snapshots as a basis for comparison between screens during future replays. If replay returns either one of the bitmaps, the Vuser will not fail.
<b>Recording Snapshot</b>	A view of the recording snapshot.
<b>Replay Snapshot</b>	A view of the replay snapshot.
<b>Stop</b>	Consider the mismatch between the snapshots to be an error. This error will be handled like all other errors and halt the execution by default. Alternatively, you can specify <b>Continue on Error</b> for a specific function as described in " <a href="#">Citrix - Troubleshooting and Limitations</a> " below.

## Citrix - Troubleshooting and Limitations

This section describes troubleshooting and limitations for Citrix Vusers.

### General limitations

- Installation of the registry patch is required for the support of all version of Citrix clients over 10.x. Additionally, you need to install Enable\_Citrix\_API.reg from the LoadRunner\dat folder on VuGen or Load Generator machines if a Citrix Client will be installed after installing LoadRunner.

- Running Citrix Vusers on virtual machines may adversely affect performance due to the sharing of physical resources.
- Citrix XenApp Desktop cannot be recorded with Citrix Web Access (formerly known as Citrix NFuse) if Desktop View (Desktop Toolbar) is enabled.
- Text recognition may not work correctly for overlapped applications on Windows 2012 servers.
- When recording Citrix Web Access (formerly known as Citrix NFuse) applications, set the window size to "No preference" in the Citrix XenApp web portal preferences page.
- When recording window size using the XenApp Plugin for Hosted Applications 11. The recording window size option does not work properly with the XenApp Plugin for Hosted Applications 11. The size of the client window is installed, but the server screen resolution is not. This is a Citrix Client limitation and will be fixed in future Citrix Client versions.

**Workaround:** When recording, set the window size equal to the local screen resolution. When replaying/load testing, set the VuGen or Load Generator screen resolution to equal the resolution used when the script was recorded. To verify the recorded resolution, view the Window property in the <Script Folder>\default.cfg file.

- The Citrix Connection Center may prevent record and replay of Citrix ICA scripts, if it is running in a different user session on the same machine.

**Workaround:** Close all instances of the *concenter.exe* process for all users. To prevent the Citrix Connection Center from starting automatically, set the *ConnectionCenter* registry key to an empty value"". This key can be found at:

For 32-bit systems: HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Run

For 64-bit systems: HKEY\_LOCAL\_MACHINE\SOFTWARE\Wow6432Node\Microsoft\Windows\Cur

## Effects and Memory Requirements of Citrix Agent

When you run Citrix Vusers with the agent installed, each Vuser runs its own process of **ctrxagent.exe**. This results in a slight reduction in the number of Vusers that can run on the server machine (about 7%).

The memory requirements per Citrix ICA Vuser (each Vuser runs its own **ctrxagent.exe** process) is approximately 4.35 MB. To run 25 Vusers, you would need 110 MBs of memory.

## Data Execution Prevention (DEP) and Citrix Agent Performance

DEP is a security feature included in Windows version XP Service Pack 2 and later. DEP can interfere with some functions of the Agent for Citrix Presentation Server and may cause VuGen to stop recording.

If you experience unusual behavior during recording in these environments, modify the DEP settings.

## Modify the Windows DEP settings

1. Open **Start > Control Panel > System**.
2. In the Advanced tab, click **Performance settings**.
3. In the Performance Options Data Execution Prevention tab, select the first option, **DEP for essential services only**.  
If you cannot change this option, click **Add**. Browse to the client program, for example IEXPLORE.EXE.
4. If neither of these options are possible, try to disable DEP completely.
  - a. Open a command prompt.
  - b. Run the following command: **bcdedit.exe /set {current} nx AlwaysOff**
  - c. Reboot the machine
  - d. Verify that the settings took effect by running the following at the command line: **BCDEdit /enum**
  - e. Verify that the last line shows **nx AlwaysOff**.

## Debugging Tips

The following section lists debugging tips for Citrix scripts.

### Single Client Installation

If you are unsuccessful in recording any actions in your Citrix session, verify that you have only one Citrix client installed on your machine. To verify that only one client is installed, open the Add/Remove Programs dialog box from the Control Panel and make sure that there is only one entry for the Citrix ICA client.

### Add Breakpoints

Add breakpoints to your script in VuGen to help you determine the problematic lines of code.

### Synchronize Your Script

If replay fails, you may need to insert synchronization functions into your script to allow more time for the desired windows to come into focus. Although you can manually add a delay using **lr\_think\_time**, we recommend that you use one of the synchronization functions discussed in "[Citrix - Automatic Synchronization](#)" on page 587.

### Continuing on Error

You can instruct Vusers to continue running even after encountering an error, such as not locating a matching window. You specify Continue on Error for individual steps.

This is especially useful where you know that one of two windows may open, but you are unsure of which. Both windows are legal, but only one will open.

## Indicate Continue on Error:

In the **Step Navigator**, right-click on the step and select **Show Arguments**. In the **Continue on Error** box, select the **CONTINUE\_ON\_ERROR** option.

In **Script view**, locate the function and add **CONTINUE\_ON\_ERROR** as a final argument, before **CTRX\_LAST**.

This option is not available for the following functions: **ctrx\_key**, **ctrx\_key\_down**, **ctrx\_key\_up**, **ctrx\_type**, **ctrx\_set\_waiting\_time**, **ctrx\_save\_bitmap**, **ctrx\_execute\_on\_window**, and **ctrx\_set\_exception**.

## Extended Log

You can view additional replay information such as:

- the total amount of GDI handles being used
- a list of the running Citrix processes (concentr.exe, receiver.exe, wfcica32.exe, wfcrun32.exe) with their PIDs and user names (if the process is not running under the LoadRunner user)
- the Citrix client name
- incompatibility warnings

To view these details, enable Extended logging in the Run-Time settings (F4 Shortcut key) **Log** tab. You can view this information in the **Replay Log** tab or in the **output.txt** file in the script's folder.

## Snapshot Bitmap

When an error occurs, VuGen saves a snapshot of the screen to the script's **output** folder. You can view the bitmap to try to determine why the error occurred.

During recording, the bitmaps generated for the **ctrx\_sync\_on\_bitmap** function are saved under the script's **data** folder. The bitmap name has the format of **hash\_value.bmp**. If synchronization fails during replay, the generated bitmap is written to the script's output folder, or if you are running it in a scenario, to wherever the output files are written. You can examine the new bitmap to determine why synchronization failed.

## Show Vusers

To show Vusers during a scenario, enter the following in the Vuser command line box: **-lr\_citrix\_vuser\_view**. In the Controller, open the Vuser Details dialog box and click **More** to expand the dialog box. Note that this will affect the scalability of the test, so this should only be done to examine a problematic Vuser's behavior.

To reduce the effect on the script's scalability, you can show the details for an individual Vuser by adding the Vuser's ID at the end of the command line: **-lr\_citrix\_vuser\_view <VuserId>**.

To open multiple Vusers, place a comma-separated list of IDs after the command line. Do not use spaces, but you may use commas or dashes. For example, 1,3-5,7 would show Vusers 1,3,4,5, and 7, but would not show Vuser 2, 6 or any Vuser with an ID higher than 7.

When recording with XenApp 5.0 using a Citrix and Web multi-protocol script, manual modifications are needed to ensure proper recording.

## Record using XenApp 5.0

### 1. Modify XenApp Settings

- a. Connect to the XenApp server through Internet Explorer.
- b. Log in using the same account that will be used during recording.
- c. Select **Preferences > Session Settings** and set **Window Size** to **No Preference**.

### 2. Update Correlation Rules

- a. Open the **HTTP Correlation** node of the Recording Options dialog box.
- b. Make sure that the **Citrix\_XenApp** rule is selected.

### 3. Modify Recording Options

- a. Open the **General > Recording** node of the Recording Options dialog box.
- b. Select **Advanced HTML** to open the Advanced HTML dialog box.
- c. Select **A script containing explicit URL's only**.

## Load Generator and Citrix XenApp 11.2 Client

- A Load Generator cannot be used as a service for the Citrix protocol when the Citrix XenApp client 11.2 is used.  
**Workaround:** Use another version of Citrix client.
- Recording a Citrix NFuse script on IE9 is supported from Citrix client version 12.1.0.44.
- Citrix Clients 11.2 and higher do not support the TCP/IP mode in the **Citrix > Login** node of the Recording Options dialog box.

## Citrix Access Gateway Support

LoadRunner supports Citrix Access Gateway (CAG) for Citrix Client versions 10.200 (or lower) and Citrix Client version 13.x.

# Click & Script Protocols

**Note:** From LoadRunner 12.00 and later, Web (Click & Script) is only supported for replay—not recording.

## Click & Script Protocols - Overview

The Click & Script protocols record Web sessions on a user-action GUI level. VuGen creates a GUI-level script that intuitively represents actions in the Web interface. For example, VuGen generates a **web\_button** function when you click a button to submit information, and VuGen generates a **web\_edit\_field** function when you enter text into an edit box.

Click & Script Vusers support non-HTML code such as Javascript on the client side. VuGen creates an intuitive script that emulates your actions on the web page, and executes the necessary Javascript code.

Click & Script Vusers handle most correlations automatically, reducing the time required to create the script. In most cases, you do not need to define rules for correlations or perform manual correlations after the recording.

Click & Script Vusers allow you to generate detailed Business Process Reports which summarize the script. For example, when you click a button to submit data, VuGen generates a **web\_button** function. If the button is an image, VuGen generates a **web\_image\_submit** function. In the following example, a Vuser clicks the **Login** button.

```
...
web_image_submit("Login",
                 "Snapshot=t4.inf",
                 DESCRIPTION,
                 "Alt=Login",
                 "Name=login",
                 "FrameName=navbar",
                 ACTION,
                 "ClickCoordinates=31,6",
                 LAST);}
```

The next section illustrates a user navigating to the Asset ExpressAdd process under the Manage Assets branch. The user navigates by clicking the text links of the desired branches, generating **web\_text\_link** functions.

```
web_text_link("Manage Assets_2",
              DESCRIPTION,
              "Text=Manage Assets",
              "Ordinal=2",
              "FrameName=main",
              ACTION,
              "UserAction=Click",
              LAST);
web_text_link("Use",
              DESCRIPTION,
              "Text=Use",
              "FrameName=main",
              ACTION,
              "UserAction=Click",
              LAST);
web_text_link("Asset ExpressAdd",
```

```

DESCRIPTION,
"Text=Asset ExpressAdd",
"FrameName=main",
ACTION,
"UserAction=Click",
LAST);

```

In the following example, the **web\_list** function emulates the selection of a list item.

```

...
web_list("Year",
    DESCRIPTION,
    "Name=Year",
    "FrameName=CalFrame",
    ACTION,
    "Select=2000",
    LAST);

```

When you click on an image that is associated with an image map, VuGen generates a **web\_map\_area** function.

```

web_map_area("map2_2",
    DESCRIPTION,
    "MapName=map2",
    "Ordinal=20",
    "FrameName=CalFrame",
    ACTION,
    "UserAction=Click",
    LAST);

```

**Note:** Click & Script Vusers do not support applets or VB script. If the Web site that is accessed by the Vusers contains these items, use the Web (HTTP/HTML) protocol.

## Click & Script Recording Tips

This section lists tips for recording click-and-script Vuser scripts.

**Note:** Some of the items below apply to specific click-and-script protocols only.

### Use the Mouse and not the Keyboard

It is preferable to click on an object with the mouse rather than using the keyboard. During recording, use only GUI objects that are within the browser's pane. Do not use any browser icons, controls, the Stop button, or menu items, such as **View > Refresh**. You may, however, use the Refresh, Home, Back and Forward buttons and the address bar.

### Do not Record Over an Existing Script

It is best to record into a newly created script—not an existing one.

## Avoid Context Menus

Avoid using context menus during recording. Context menus are right-click menus which pop up when clicking certain objects in a graphical user interface.

## Avoid Working in Another Browser While Recording

While recording, do not work in any browser window other than the browser windows opened by VuGen.

## Wait for Downloads

Wait for all downloads to complete before doing any action, such as clicking on a button or filling in a text field.

## Wait for Pages to Load

During recording, it is best to wait for the page to load completely before doing the next step. If you did not wait for all of the pages to load, record the script again.

## Navigate to the Start Page

If the last page in an action does not contain the links and buttons that were available at the start of the iteration, then the next iteration will fail. For example, if the first page has a text link **Book A Flight**, make sure to navigate to the appropriate page at the end of your recording, so that the same link will be visible at the end of the business process.

## Use a Higher Event Configuration Level

Record the business process again using the **High** event configuration level. For more information on changing the event configuration level, see "[Click & Script Troubleshooting and Limitations](#)" on [page 610](#).

## Disable Socket Level Recording

In certain cases, the capturing of the socket level messages disrupts the application. For most recordings, socket level data is not required. To prevent the recording of socket level data, disable the option in the recording options. For more information, see "[GUI Properties > Advanced Node](#)" on [page 219](#).

## Enable the "Record rendering-related property values" Option

If the client-side scripts of the application use a lot of styling activities, enable the **Record rendering-related property values** option before recording the script. For example, enable this option to record additional DOM properties such as **offsetTop**. Note that enabling this option may decrease the recording speed. You can enable the option by selecting **Recording Options > GUI Properties > Advanced**. For more information, see "[GUI Properties > Advanced Node](#)" on [page 219](#).

# Click & Script - Replay Tips

This section lists tips for replaying click-and-script Vuser scripts.

**Note:** Some of the items below apply to specific click-and-script protocols only.

## Do not Reorder Statements in a Recorded Script

Do not change the order of the statements within a recorded script. Also, copying segments of code from one Action to another is not recommended.

## Convert non-ASCII Characters

If your links contain non-ASCII characters, you should instruct VuGen to convert the data to or from the UTF-8 format.

### Enable UTF-8 Conversion

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the Advanced Options dialog box.
3. Locate the **Convert from/to UTF-8** option and set it to **Yes**.

Alternatively, view the list of options that is displayed when a link is not found. Enter the displayed text as-is, such as the hex escape sequences \xA0 or any other non-standard format.

## Run the Same Sequence of Actions Twice

In some cases, you can perform a certain process only once—such as deleting a user from the database. Replay will fail after the first iteration because the action is no longer valid. Verify that your business process can be repeated more than once with the same data.

## Set Unique Image Properties

In the Step Navigator, double click on the previous image step to open its properties. If the **Id**, **Name**, and **Alt** properties are empty, provide further identification of the image, such as its file name in the **Src** property.

Alternatively, you can add an **Ordinal** argument to specify the occurrence number of the image on that page. The **Ordinal** argument uniquely identifies each image on the page where all other identification arguments are not unique. For more information, see the Function Reference ([Help > Function Reference](#)).

## Check the Step's Description

If you receive a **GUI Object is not found** error, check the Output pane for a list of the objects in the problematic step. In some cases, the object description changes slightly from run to run.

There are several solutions:

- If the new value is stable, open the script in the Editor and manually modify the value of the step's **DESCRIPTION** argument.
- If the description changes from run to run, you can use a regular expression in the **DESCRIPTION** argument. For more information, see the Function Reference ([Help > Function Reference](#)).
- Alternatively, replace the problematic object description property, such as **Name**, with the **Ordinal** property. For more information, see the Function Reference ([Help > Function Reference](#)).

Reference).

#### ThreadingModel

Replay of COM script in VuGen fails when the dll registration is missing the **ThreadingModel** string under the **InprocServer32** folder of the GUID.

## Click & Script Miscellaneous Tips

The following additional tips may help you in troubleshooting problems that you experience with click-and-script Vuser scripts.

**Note:** Some of the items below apply to specific click-and-script protocols only.

### Search for Warnings

Search for warnings or alerts in the Output pane.

### Verify the Response

Verify the response of the previous step is correct using **web\_reg\_find**. For more information, see the Function Reference (**Help > Function Reference**).

### Use Alternate Navigation

For problematic steps or those using Java applets, use **Alternative Navigation** to replace the Web step with an HTTP level step. Note that the HTTP level steps may require manual correlations. To perform Alternative Navigation, select a step in the **Step Navigator**, or the text in Script View, and select **Replace with alternative navigation** from the right-click menu.

### Working with the Kerberos Protocol

If you are using the Kerberos Protocol for authentication, you must customize VuGen to properly convene authorization sessions. Advanced users can attempt to perform this customization themselves.

In order for the Kerberos Protocol to work properly, create a krb5.ini file and put it in an available folder. Save the full path name of krb5.ini into the KRB5\_CONFIG environment variable.

The krb5.ini file should contain detailed information about each domain (KDS and AS addresses) and trust chains.

For more information, contact HP software support.

## Click & Script Enhancements

The following section describes several enhancements that can assist you in creating your script.

Most of the features described below are enhancements to the API functions. For detailed information about the functions and their arguments, see the Function Reference (**Help > Function Reference**) or click F1 on any function.

### Adding conditional steps

The Web (Click & Script) functions, **web\_xxxx**, allow you to specify conditional actions during replay. Conditions are useful, for example, if you need to check for an element and perform an action only if the element is found.

For example, suppose you perform an Internet search and you want to navigate to all of the result pages by clicking Next. Since you do not know how many result pages there will be, you need to check if there is a Next button, indicating another page, without failing the step. The following code adds a verification step with a notification—if it finds the Next button, it clicks on it.

```
While (web_text_link("Next",
DESCRIPTION,
    "Text=Next",
    VERIFICATION,
    "NotFound=Notify",
    ACTION,      "UserAction=Click",
LAST) == LR_PASS);
```

For details about the syntax and use of the VERIFICATION section, see the Function Reference ([Help > Function Reference](#)).

### Checking a page title

In **web\_browser** steps, you can use the title verification recording option to make sure that the correct page is downloaded. You can instruct the Vuser to perform this check automatically for every step or every navigation to a new top level window.

In addition, you can manually add title verifications to your script at the desired locations, using both exact and regular expression matches.

```
web_browser("test_step",
DESCRIPTION,
...
VERIFICATION,
    "BrowserTitle=Title",
    ACTION,]
,
LAST);
```

For more information, see the Function Reference ([Help > Function Reference](#)).

You can set title verification options directly from within the Recording options. For more information, see the section about recording with Click & Script.

### Text check verification

Using text checkpoints, you can verify that a text string is displayed in the appropriate place on a Web page or application and then perform an action based on the findings. You can check that a text string exists (**ContainsText**), or that it does not exist (**DoesNotContainText**), using exact or regular expression matching.

For example, suppose a Web page displays the sentence "Flight departing from New York to San Francisco". You can create a text checkpoint that checks that the words "New York" are displayed between "Flight departing from" and "to San Francisco". (In this example, you would need to use regular expression criteria.)

To implement these checkpoints, you add the Text Check related arguments to the VERIFICATION section of the step. During replay, Vusers search the innerText of the browser's HTML document and any child frames. The **NotFound** argument specifies the action to take if verification fails, either because the object was not found or because the text verification failed: Error, Warning, or Notify.

You can manually add text verifications to your script for existing steps. Place the text verification after the step that generated the element.

The text validation arguments are valid for the following Action functions: **web\_browser**, **web\_element**, **web\_list**, **web\_text\_link**, **web\_table**, and **web\_text\_area**.

**Note:** You can only use the same type of text verification once per step (for example, **ContainsText** twice). If you want to check for multiple texts, separate them into several steps. You can, however, use different verifications in the same step (for example, **ContainsText =**; **DoesNotContainText**). In this case, all conditions have to be met in order for the step to pass.

In the following example, the verification arguments check that we were not directed from www.acme.com to the French version of the website, acme.com/fr.

```
web_browser("www.acme.com",
            ACTION,
            "Navigate=http://www.acme.com/",
            LAST);
web_browser("Verify",
            VERIFICATION,
            "ContainsText=Go to Acme France",
            "DoesNotContainText=acme.com in English",
            LAST);
```

#### Saving a Java script value to a parameter

The **EvalJavaScript** argument lets you evaluate Java Script on the Web page.

Suppose you want to click on a link which has the same name as the page title. The following example evaluates the document title and uses it in the next **web\_text\_link** function.

```
web_browser("GetTitle",
            ACTION,
            "EvalJavaScript=document.title;",
            "EvalJavaScriptResultParam=title",
            LAST);
web_text_link("Link",
            DESCRIPTION,
            "Text={title}",
            LAST);
```

#### Working with custom descriptions

Suppose you want to randomly click a link that belongs to some group. For example, on **hp.com** you want to randomly select a country. Regular description matching will not allow this type of operation. However, using a custom description argument, you can identify the group with an

attribute that is common to all the links in the group.

Using the custom description argument, you specify any attribute of the element, even those that are not predefined for that element. During replay, the Vuser searches for those attributes specified in the DESCRIPTION section. Replay will not fail on any unknown argument in the DESCRIPTION section.

For example, to find the following hyperlink:

`<a href="yahoo.com" my_attribute="bar">Yahoo</a>`, use:

```
web_text_link("yahoo",
    DESCRIPTION,
    "Text=yahoo",
    "my_attribute=bar",
    LAST);
```

In the following example, since all the relevant links have the same class name, newmerc-left-ct, you can perform a random click using the following code:

```
web_text_link("Click",
    DESCRIPTION,
    "Class=newmerc-left-ct",
    "Ordinal=random",
    LAST);
```

The following functions do not support the custom description arguments: `web_browser`, `web_map_area`, `web_radio_group`, and `web_reg_dialog`.

### Copying text to the clipboard

VuGen lets you copy text from a browser to the clipboard. This functionality is available in both the Page view and Page Source view. For details on how to copy the text to the clipboard, see ["How to Work with Snapshots" on page 88](#).

## Click & Script API Notes

This section lists general notes about the Web functions. Note that you can specify a regular expression for most object descriptions, by preceding the text with "/RE" before the equals sign. See the Function Reference ([Help > Function Reference](#)) for more details. For example:

```
web_text_link("Manage Assets",
    DESCRIPTION,
    "Text/RE=(Manage Assets)|(Configure Assets)",
    ACTION,
    "UserAction=Click",
    LAST);
```

### Ordinals

The Ordinal attribute is a one-based index to distinguish between multiple occurrences of objects with identical descriptions. In the following example, the two recorded `web_text_link` functions

have identical arguments, except for the ordinal. The ordinal value of 2, indicates the second occurrence.

```
web_text_link("Manage Assets",
    DESCRIPTION,
    "Text=Manage Assets",
    "FrameName=main",
    ACTION,
    "UserAction=Click",
    LAST);
web_text_link("Manage Assets_2",
    DESCRIPTION,
    "Text=Manage Assets",
    "Ordinal=2",
    "FrameName=main",
    ACTION,
    "UserAction=Click",
    LAST);
```

## ***Empty Strings***

There is a difference between not specifying an argument and specifying it as an empty string. When you do not specify an argument, VuGen uses the default value or ignores it. When you list an argument, but assign it an empty string as a value, VuGen attempts to find a match with an empty string or no string at all. For example, omitting the id argument instructs VuGen to ignore the id property of the HTML element. Specifying "ID=" searches for HTML elements with no id property or with an empty ID.

```
web_text_link("Manage Assets_2",
    DESCRIPTION,
    "Text=Manage Assets",
    "Id=",
    "FrameName=main",
    ACTION,
    "UserAction=Click",
    LAST);
```

# **Click & Script Troubleshooting and Limitations**

This section describes troubleshooting and limitations for click-and-script protocols.

**Note:** Some of the items below apply to specific click-and-script protocols only.

## **Recording Issues and Limitations**

### **Browser support**

- Only Internet Explorer is supported for Click & Script protocols. To record browser activity on Firefox, use the Web (HTTP/HTML) protocol.

- The Citrix agent cannot capture text from Java-based applications and Internet Explorer version 9 and higher.

### Language Support

- Recording an application in a specific language (e.g., French, Japanese) must be performed on a machine whose default locale (in **Settings > Control Panel > Regional Options**) is the same language
- Support of right-to-left languages is limited (e.g., bi-directional or reversed text may not be processed as expected). This is defined by the default operating system translation table.
- The locale of the load-generator machine, must be configured to be the same as that of the recording machine. It cannot be assumed that the Linux default character set is the same as in Windows, even for US-English machines, and this has to be explicitly verified. For example, the default character set on Linux, is UTF-8.

### Application behaves differently while being recorded

If your application behaves differently during recording, than it does without recording, you should determine if the recording problem is unique to Web. The effect may be that a Web page will not load, part of the content is missing, a popup window does not open, and so forth.

Create a new Web (HTTP/HTML) script and repeat the recording.

In the event that the recording fails in Web (HTTP/HTML), we recommend that you disable socket level recording (see "[Click & Script Recording Tips](#)" on page 603).

The problem may be the result of an event listener. Use trial and error to disable event listeners in the **Web Event Configuration** Recording Options, and then re-record your session as a Web user.

### Certain Click & Script steps do not generate properly

After recording a script, if not all steps are correctly generated, the problem may be due to the **Windows Component > Internet Explorer Enhanced Security Configuration**.

Remove **Internet Explorer Enhanced Security Configuration** by selecting **Control Panel > Add or Remove Programs > Add or Remove Windows Components** and re-record your script.

### Disable an Event Listener

1. Click **Record > Recording Options** to open the Recording Options dialog box.
2. Select the **GUI Properties > Web Event Configuration** node.
3. Click **Custom Settings** and expand the **Web Objects** node. Select an object.
4. Select **Disabled** from the list in the **Record** column for the relevant Web object. If the recording still does not work, enable the listener you previously disabled, and try disabling another one. Repeat these steps until your recording succeeds.

### Dynamic menu navigation was not recorded

A dynamic menu is a menu that dynamically changes depending on where you select it. If the dynamic menu navigation was not recorded, record again using "high" event configuration mode. These settings can be found in the **Recording Options > GUI Properties > Web Event Configuration** node.

#### Certain user actions were not recorded

Check if there is a Java applet running inside the browser. If not, record the script with the Web (HTTP/HTML) protocol.

### Replay Issues

#### GUI object not found

Does the error occur at the beginning of the second iteration?

If the error occurs at the beginning of the second iteration's Action section, it is probably the result of a starting page that was present for the first iteration, but missing for the second one. If the last page in an action does not contain the links and buttons that were available at the start of the iteration, then the next iteration will fail. For example, if the first page has a text link **Book A Flight**, make sure to navigate to the appropriate page, so that the same link will be visible at the end of the business process.

Is it a text link containing non-ASCII characters?

If the problem occurs with non-ASCII characters, you should instruct VuGen to convert the data to a suitable character set.

### Enable Data Conversion on Windows Machines

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the Advanced Options dialog box.
3. Locate **Charset Conversions by HTTP** in the Web (Click & Script) > General options, and set it to **Yes**.

### Enable UTF-8 conversion for Linux Machines

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the **Advanced Options** dialog box.
3. Locate **Convert from/to UTF-8** in the General options and set it to **Yes**

Alternatively, view the list of alternatives that are displayed when a link is not found. Enter the displayed text as-is, such as hex escape sequences \xA0 or any other non-standard format.

Can you run the same sequence of actions twice in the application?

In some cases, you can only perform a certain process once, such as deleting a user from the database. Replay will fail after the first iteration, because the action is no longer valid. Verify that your business process can be repeated in the application more than once with the same data, without recording again.

Were the image properties 'Id', 'Name' and 'Alt' empty?

In the **Step Navigator**, double click on the previous image step to open its properties. If the **Id**, **Name**, and **Alt** properties are empty, provide further identification of the image, such as its file name in the **Src** property.

Alternatively, you add an **Ordinal** argument to specify the occurrence number of the image on that page. The **Ordinal** argument uniquely identifies each image on the page where all other identification arguments are not unique. For more information, see the Function Reference (**Help > Function Reference**).

Did the step's description change?

Check the Output pane for a list of the objects in the problematic step. In some cases, the object description changes slightly from run to run.

There are several solutions:

- If the new value is stable, open the Script View and manually modify the value of the step's DESCRIPTION argument(s).
- If the description changes from run to run, you can use a regular expression in the DESCRIPTION argument(s). For more information, see the Function Reference (**Help > Function Reference**).
- Alternatively, replace the problematic object description property, such as Name, with the Ordinal property. For more information, see the Function Reference (**Help > Function Reference**).

Did the page load completely during recording?

During recording, it is best to wait for the page to load completely before doing the next step. If you did not wait for all of the pages to load, record the script again.

### Replay failure

If the replay is failing at a particular step, check the step description. VuGen sometimes reads a single space as a double space. Make sure that there are no incorrect double spaces in the string.

## Miscellaneous Issues

### Out of memory error in JavaScript

Increase the JavaScript memory in the run-time settings.

### Increase the JavaScript Memory Size

1. Select **Replay > Run-Time Settings** and select the **Internet Protocol > Preferences** node.
2. Click **Options** to open the Advanced Options dialog box.
3. Locate the **Memory Management JavaScript Runtime Memory Size (Kb)** and **Memory Management JavaScript Stack Memory Size (Kb)** options.

4. Increase the memory sizes to 512Kb or higher.

#### **VuGen displays JavaScript errors**

If VuGen displays JavaScript errors in the Output pane, enable IE (Internet Explorer) script errors in order to verify that the Javascript itself does not contain errors.

### **Show Script Errors**

1. Open Internet Explorer.
2. Select **Tools > Internet Options** and click the **Advanced** tab.
3. Under **Browsing**, select the **Display a notification about every script error** check box.
4. Rerun the application in IE. If IE displays script errors, then there is a problem with the JavaScript application. If it is not possible to fix the application, you can safely ignore the corresponding replay errors.

#### **Problems following parameterization**

If you encounter problems only after you have parameterized values, verify that the values are valid for your application. Perform business process with the value of the parameter and verify that the application accepts it.

#### **Problems with applications that utilize styling actions**

If the client-side scripts of the application use a lot of styling activities, you should record the script again after enabling the **Record rendering-related property values** option. This enables the recording of additional DOM objects.

### **Enable the "Record rendering-related property values" Option**

1. Select **Recording > Recording Options** and select the **GUI Properties > Advanced** node.
2. Select the **Record rendering-related property values** check box.

Re-record the Vuser script.

## **COM Protocol**

### **COM Protocol Overview**

When you record COM client applications, VuGen generates functions that describe COM client-server activity. The recorded script contains interface declarations, API calls and instance calls to methods. Each COM function begins with an **Irc** prefix. You can configure the programming language in which to create a Vuser script as either C or Visual Basic.

For each COM Vuser script, VuGen creates the following:

- Interface pointer and other variable declarations in the interfaces.h file.
- Function calls that you can record in the vuser\_init, actions or vuser\_end sections of the Vuser file.
- A user.h file containing the translation of the Vuser script into low level calls.

## COM Technology Overview

This section provides an outline of COM technology. This should be enough to get you started with COM Vuser scripts. See Microsoft Developer's Network (MSDN) and other documentation for further details.

COM (Component Object Model) is a technology for developing reusable software components ("plug-ins"). DCOM (Distributed COM) allows use of COM components on remote computers. Microsoft transaction servers (MTS), Visual Basic and Explorer all use COM/DCOM technology. Thus, the application you are testing may use COM technology indirectly, even though you don't know it. You will probably have to include some, but certainly not all, of the COM calls made by your application in the Vuser script.

### Objects, Interfaces and Type Libraries

COM objects are binary code modules. Each COM object implements one or more interfaces that allow client programs to communicate with it. You need to know about these interfaces in order to follow the COM calls in the Vuser scripts. Type libraries, used as a reference for accessing COM interface methods and parameters, contain descriptions of COM objects and interfaces. Each COM class, interface, and type library is identified by a Global Unique Identifier (GUID).

### COM Interfaces

A COM interface provides a grouped collection of related methods. For example, a **Clock** object may have **Clock**, **Alarm** and **Timer** interfaces. Each interface has one or more methods. For example the **Alarm** interface may have **AlarmOn** and **AlarmOff** methods.

An interface may also have one or more properties. Sometimes, the same function may be performed by calling a method or by setting or getting the value of a property. For example, you can set the **Alarm Status** property to **On** or call the **AlarmOn** method.

A COM object may support many interfaces. The **IUnknown** interface is implemented by all components and is used to find out about other interfaces. Many components also implement the **IDispatch** interface, which exposes all other interfaces and methods of the object, allowing implementation of COM automation in scripting languages.

### COM Class Context and Location Transparency

COM objects can run on the same machine as the client application, or on a remote server. COM objects that an application creates may be in a local library, a local process or a remote machine ("Remote Object Proxy"). The location of the COM object, known as the "Context," can be transparent to the application. Most users apply the Vusers to check the load on remote servers. Therefore, objects accessed by Remote Object Proxy are usually the most relevant for these tests.

## COM Data Types

COM also provides several special data types, including safe arrays, BSTR strings and variants. You may need to use these data types for debugging, parameterization and similar tasks.

# COM Vuser Script Structure

VuGen COM Vuser scripts are structured in a special way to meet the needs of COM interfaces.

## Interface Methods

Calls to interface methods have the following names and syntax conventions:

```
lrc_<interface name>_<method name>(instance,...);
```

Note that the instance is always the first parameter passed.

The vendors of the respective COM components usually supply documentation for the interface functions.

## Interface Pointers

The interface header file defines the interface pointers, as well as other variables, that can be used in the script. Each interface has an Interface ID (IID) which uniquely identifies the interface.

The format of the interface definition is:

```
<interface type>*<interface name> = 0; //"{<IID of the interface type>}"
```

In the following example, the interface type is IDispatch, the name of the interface instance is IDispatch\_0, and the IID of IDispatch type is the long number string:

```
IDispatch* IDispatch_0= 0;//"{00020400-0000-0000-0000-00000000046}"
```

## Vuser Script Statements

The COM Vuser script consist of code that creates object instances, retrieves interface pointers and calls the interface methods. Each user action may generate one or more COM calls. Each COM call is coded by VuGen as a group of statements. Each such group is contained in a separate scope enclosed in braces. Several different statements prepare for the main call by assigning values and performing type conversions. For example, the group of calls needed to create an object may look like this:

```
{
GUID pClSID = lrc_GUID("student..1");
IUnknown * pUnkOuter = (IUnknown*)NULL;
unsigned long dwClSIDContext = lrc_ulong("7");
GUID riid = IID_IUnknown;
lrc_CoCreateInstance(=;pClSID, pUnkOuter, dwClSIDContext, =;riid, (void**)=;IUnkn
wn_0, CHECK_HRES);
}
```

## Error Checking

Each COM method or API call returns an error value. VuGen will set a flag to check or not to check errors during replay, depending upon whether the call succeeded during the original recording. The

flag appears as the last argument of the function call and has these values:

<b>CHECK_HRES</b>	This value is inserted if the function passed during recording and errors should be checked during replay.
<b>DONT_CHECK_HRES</b>	This value is inserted if the function failed during recording and errors should not be checked during replay.

## COM Sample Vuser Scripts

This section shows examples of how VuGen emulates a COM client application. It is divided up into the basic COM script operations. Each type of operation is done within a separate scope.

### Instantiation of the Object

To use a COM object, the application must first instantiate it and get a pointer to an interface of that object.

#### VuGen does the following to instantiate an object

1. VuGen calls lrc\_GUID to get a unique ProgID for the object, to be stored in pClSID:

```
GUID pClSID = lrc_GUID("student..1");
```

**pClSID** is the unique global CLSID of the object, which was converted from the **student.student.1** ProgID.

2. If the unknown interface pointer is a pointer to an aggregated object, VuGen retrieves the pointer to that object, or else it sets it to NULL:

```
IUnknown * pUnkOuter = (IUnknown*)NULL;
```

3. VuGen sets the contexts of the object to be created:

```
unsigned long dwClSIDContext = lrc_ulong("7");
```

**dwClSIDContext** contains the context of the object (in process, local, remote or combinations of these.)

4. VuGen sets a variable to hold the requested interface ID, which is IUnknown in this case:

```
GUID riid = IID_IUnknown;
```

**riid** contains the interface ID of the **IUnknown** interface.

5. After the input parameters are prepared, a call to lrc\_CoCreateInstance creates an object using the parameters defined in the preceding statements. A pointer to the IUnknown interface is assigned to output parameter **IUnknown\_0**. This pointer is needed for subsequent calls:

```
lrc_CoCreateInstance(=;pClSID, pUnkOuter, dwClSIDContext, =;riid, (void**)&IUnknown_0, CHECK_HRES);
```

The input parameters were prepared and explained above. Since the call succeeded, VuGen sets error checking on during the user simulation by inserting the **CHECK\_HRES** value. The call returns a pointer to the **IUnknown** interface in **IUnknown\_0**, that can be used in subsequent calls.

## Retrieving an Interface

After creating an object, VuGen has access only to the **IUnknown** interface . VuGen will use the **IUnknown** interface for communicating with the object. This is done using the **QueryInterface** method of the **IUnknown** standard interface. The first parameter in a VuGen method call is the interface instance. In this case it is the **IUnknown\_0** pointer set previously by **CoCreateInstance**. The **QueryInterface** call requires as input the ID of the interface to be retrieved, and returns a pointer to the interface designated by that ID.

## Get the Interface

- First, VuGen sets a parameter, **riid**, equal to the ID of the **Istudent** interface:

```
GUID riid = IID_Istudent;
```

- A call to **QueryInterface** assigns a pointer to the **Istudent** interface to output parameter **Istudent\_0** if the **Istudent** object has such an interface:

```
lrc_IUnknown_QueryInterface(IUnknown_0, =;riid, (void**)&Istudent_0, CHECK_HRES);
```

## Using an Interface to Set Data

Here is an example of using the methods of the interface to set data. Suppose that in the application, the user is supposed to input a name. This activates a method for setting the name. VuGen records this in two statements. One statement is used for setting up the name string and the second one sets the name property.

## Set up the Entire Function Call

- First, VuGen sets a variable (Prop Value) equal to the string. The parameter is of type **BSTR**, a string type used in COM files:

```
BSTR PropValue = lrc_BSTR("John Smith");
```

In subsequent stages, you will probably parameterize this call, replacing "John Smith" with a parameter, so that different names are used each time the Vuser script is run.

- Next, VuGen calls the **Put\_Name** method of the **Istudent** interface to enter the name:

```
lrc_Istudent_put_name(Istudent_0, PropValue, CHECK_HRES);
```

## Using an Interface to Return Data

Returning data from an application is different than entering the data, because you might want to store these values and use them as inputs in subsequent calls for parameterization.

## The following is an example of what VuGen may do when the application retrieves data

1. Create a variable of the appropriate type (in this case a BSTR) that will contain the value of the property.

```
BSTR pVal;
```

2. Get the value of the property, in this case a name, into the **pVal** variable created above, using the `get_name` method of the **Istudent** interface in this example.

```
lrc_Istudent_get_name(Istudent_0, =;pVal, CHECK_HRES);
```

3. VuGen then generates a statement for saving the values.

```
//lrc_save_BSTR("param-name",pVal);
```

The statement is commented out. You can remove the comments and change <param-name> to a variable with a meaningful name to be used for storing this value. VuGen will use the variable to save the value of **pVal** returned by the previous call. You can then use the variable as a parameterized input in subsequent calls to other methods.

## The IDispatch Interface

Most COM objects have specific interfaces. Many of them also implement a general-purpose interface called **IDispatch**, which VuGen translates in a special way. **IDispatch** is a "superinterface" that exposes all of the other interfaces and methods of a COM object. Calls to the **IDispatch:Invoke** method from VuGen scripts are implemented using **lrc\_Dispatch** functions. These calls are constructed somewhat differently from calls to other interfaces.

The **IDispatch** interface **Invoke** method can execute a method, it can get a property value, or it can set a value or reference value for a property. In the standard **IDispatch:Invoke** method these different uses are signaled in a **wFlags** parameter. In the VuGen implementation they are implemented in different procedure calls that invoke a method or put or get a property.

For example, a call to **IDispatch** to activate the **GetAgentsArray** method may look like this:

```
retValue = lrc_DispatchMethod1((IDispatch*)IDispatch_0, "GetAgentsArray", /*locale*/1033, LAST_ARG, CHECK_HRES);
```

The parameters in the above call are:

<b>IDispatch_0</b>	This is the pointer to the <b>IDispatch</b> interface returned by a previous call to the <b>IUnknown:QueryInterface</b> method.
<b>GetAgentsArray</b>	This is the name of the method to invoke. Behind the scenes, VuGen will get the ID of the method from the name.
<b>1033</b>	This is the language locale.
<b>LAST_ARG</b>	This is a flag to tell the <b>IDispatch</b> interface that there are no more arguments.
<b>CHECK_HRES</b>	This flag turns on checking of HRES, since the call succeeded when it was recorded.

In addition, there might be another parameter, OPTIONAL\_ARGS. This signals that in addition to any standard parameters, VuGen is sending some optional arguments. Each optional argument consists of a pair giving the ID or name of the argument and its value. For example, the following call to lrc\_DispatchMethod passes optional arguments "#3" and "var3":

```
{
    GUID riid = IID_IDispatch;
    lrc_IOptional_QueryInterface(IOptional_0, =;riid, (void**)=;IOptional_0,
CHECK_HRES);
}
{
    VARIANT P1 = lrc_variant_short("47");
    VARIANT P2 = lrc_variant_short("37");
    VARIANT P3 = lrc_variant_date("3/19/1901");
    VARIANT var3 = lrc_variant_scode("4");
    lrc_DispatchMethod((IDispatch*)IOptional_0, "in_out_optional_args", /*locale
*/1024, =;P1, =;P2, OPTIONAL_ARGS, "#3", =;P3, "var3", =;var3, LAST_ARG, CHECK_H
RES);
}
```

The different **lrc\_Dispatch** methods that use the **IDispatch** interface are detailed in the .

## Type Conversions and Data Extraction

As shown in the above example, many COM parameters are defined as variants. To extract these values, VuGen uses a number of conversion functions, derived from the equivalent COM functions. The full list is given in the . Previously, we showed how the **lrc\_DispatchMethod1** call was used to retrieve an array of name strings:

```
VARIANT retValue = lrc_variant_empty();
retValue = lrc_DispatchMethod1((IDispatch*)IDispatch_0, "GetAgentsArray", /*locale*/
1033, LAST_ARG, CHECK_HRES);
```

The following example now shows how VuGen gets the strings out of **retValue**, which is a variant that will be read as an array of strings.

First, VuGen extracts the BSTR array from the variant:

```
BstrArray array0 = 0;
array0 = lrc_GetBstrArrayFromVariant(=;retValue);
```

With all the values in array0, VuGen provides you with code that you can use to extract the elements from the array for later use in parameterization, as in the example below:

```
//GetElementFrom1DBstrArray(array0, 0); // value: Alex
//GetElementFrom1DBstrArray(array0, 1); // value: Amanda
....
```

VuGen has numerous type conversion functions and functions for extracting conventional types from variants. These are detailed in the Function Reference (**Help > Function Reference**).

## Selecting COM Objects to Record

The application you are testing may use a great many COM objects. Only a few may actually create load and may be important for the load test. Thus, before you record a COM application, you should select the objects you want to record for the load test. VuGen allows you to browse for objects from type libraries that it can read on the local machine and on other computers in the network.

### Deciding Which Objects to Use

There are several ways to decide which COM objects should be included in the test. Try to determine which remote objects are used by the software. If you are unsure which objects to use, try using the default filter. The Environments branch of the filter includes calls to three sets of objects (ADO, RDS and Remote) that are likely to generate load on remote servers.

You can also check the actual calls to refine the filter. After you have recorded the test, you can save the file and look in the **data** folder that VuGen creates for a file named **lrc\_debug\_list\_<nnn>.log**, where **nnn** is the process number. This log file contains a listing of each COM object that was called by the recorded application, regardless of whether or not the recording filter included that object. Only calls that generate load on the server should be included for recording.

For example, the following is a local COM of the Visual Basic library:

```
Class JetES {039EA4C0-E696-11D0-878A-00A0C91EC756}
was loaded from type library "JET Expression Service Type Library"
({2358C810-62BA-11D1-B3DB-00600832C573} ver 4.0)
```

It should not be added since it does not generate load on the server.

Likewise, since the OLE DB and Microsoft Windows Common Controls are local objects, the following are examples of classes and libraries that are not going to place any load on the server and should not be recorded:

```
Class DataLinks {2206CDB2-19C1-11D1-89E0-00C04FD7A829}
was loaded from type library "Microsoft OLE DB Service Component 1.0 Type Library"
({2206CEB0-19C1-11D1-89E0-00C04FD7A829} ver 1.0)
Class DataObject {2334D2B2-713E-11CF-8AE5-00AA00C00905}
was loaded from type library "Microsoft Windows Common Controls 6.0 (SP3)"
({831FDD16-0C5C-11D2-A9FC-0000F8754DA1} ver 2.0)
```

However, for example, a listing such as the following indicates a class that should be recorded since it does generate load on the server:

```
Class Order {B4CC7A90-1067-11D4-9939-00105ACECF9A}
was loaded from type library "FRS"
({B4CC7A8C-1067-11D4-9939-00105ACECF9A} ver 1.0)
```

Calls to classes of the **FRS** library, used for instance in the **flight\_sample** that is installed with VuGen, use server capacity and should be recorded.

If a COM object itself calls other COM objects, all the calls will be listed in the type information log file. For example, every time the application calls an **FRS** class function, the **FRS** library calls the **ActiveX Data Object (ADO)** library. If several functions in such a chain are listed in a filter, VuGen

records only the first call that initiates the chain. If you selected both **FRS** and **ADO** calls, only the **FRS** calls will be recorded.

On the other hand, if you select only the **ADO** library in the filter, then calls to the **ADO** library will be recorded. It is often easier to record the call to the first remote object in the chain. In some cases, however, an application may use methods from several different COM objects. If all of them use a single object that puts a load on the server, you could only record the final common object.

### Which Objects Can be Selected

VuGen can only record objects if it can read their type libraries. If the type libraries were not installed in the system or VuGen cannot find them, the COM objects will not be listed in the Recording Options dialog box. If they are used by your application, VuGen will not be able to identify these objects and will identify them as **INoTypeInfo** in the files.

### Which Interfaces Can be Excluded

For each object, the Recording Options dialog box will show you all interfaces that are listed in the Type Library, and allow you to specify inclusion or exclusion of each one. However, **ADO**, **RDS** and Remote Objects can be included in the filter as a group. The filter will not show the individual objects of those environments or their interfaces. Objects that you included from type libraries may also have interfaces that are not listed in the type library and therefore not shown in the Recording Options dialog. After generating a VuGen script, you can identify these interfaces in the script and get their GUID numbers from the interfaces.h file that VuGen generates. Using this information, you can exclude the interfaces as explained in "["COM/DCOM > Filter Node" on page 180](#)".

## Database Protocols

### Database Protocols Overview

Suppose that you have a database of customer information that is accessed by customer service personnel located throughout the country. You use Database Vusers to emulate the situation in which the database server services many requests for information. A Database Vuser could:

- Connect to the server
- Submit an SQL query
- Retrieve and process the information
- Disconnect from the server


You distribute several hundred Database Vusers among the available load generators, each Vuser accessing the database by using the server API. This enables you to measure the performance of your server under the load of many users.

The program that contains the calls to the server API is called a Database Vuser script. It emulates the client application and all of the actions performed by it. The Vusers execute the script and emulate user load on the client/server system. The Vusers generate performance data which you can analyze in report and graph format.

VuGen supports the following database types: CtLib, DbLib, Oracle, ODBC, and DB2-CLI. The resulting script contains LRD functions that describe the database activity.

## VuGen Database Recording Technology

VuGen creates Database Vuser scripts by recording all the activity between a database client and a server. VuGen monitors the client end of the database and traces all the requests sent to and received from the database server.



Like all other Vusers created using VuGen, Database Vusers communicate with the server without relying on client software. Instead, each Database Vuser executes a script that executes calls directly to server API functions.



You create Database Vuser scripts in a Windows environment using VuGen. Once you create a script, you can assign it to Vusers in both Windows and Linux environments.

Users working in a Linux only environment can create Database Vuser scripts through programming using VuGen templates as the basis for a script. For information about programming Database Vuser scripts on Linux, see "[Creating and Running Scripts in Linux](#)" on page 982.

## Database Grids

When you record or replay a Vuser script, the data that is returned by each query is displayed in a data grid. In a Vuser script, the existence of a data grid is indicated by a **GRID** statement. VuGen displays data grids in either the Data Grids pane or the Snapshot pane.

- For an introduction to the Snapshot pane, see "[Snapshot Pane - Overview](#)" on page 85.
- For details on how to work with the Snapshot pane, see "[How to Work with Snapshots](#)" on page 88.
- For details on the Snapshot pane UI, see "[Snapshot Pane](#)" on page 126.

### To correlate a value in a data grid:

Display the data grid in the Snapshot pane, right-click in a cell inside the data grid, and select **Create Correlation**.

### To save the data in a data grid to a file:


Display the data grid in the Snapshot pane or the Data Grids pane, right-click in any cell in the data grid, and select **Save Grid To File**.

### To copy the text from a cell in a data grid to the clipboard:

Display the data grid in the Snapshot pane or in the Data Grids pane, right-click in the cell in the data grid, and select **Copy Selection**.

### To search for data inside a data grid:

1. Display the data grid in the Snapshot pane, and click **Search > Quick Find** to open the Search dialog box.
2. Click **Include in Search**, and then select the **Snapshots** check box.



## Flex (RTMP/AMF) Protocol

### Flex Overview

**Note:** This topic applies to Flex Vuser scripts only.

The Flex Vuser protocol emulates communication between a client server application that uses the Flex collection of technologies.

This topic provides an overview of various topics relating to Flex Vuser scripts.

#### What is Flex

Flex is a collection of technologies that provides developers with a framework for building RIAs (Rich Internet Applications) based on the Flash Player.

RIAs are lightweight online programs that provide users with more dynamic control than with a standard Web page. Like Web applications built with Ajax, Flex applications are generally more responsive, because the application does not need to load a new Web page every time the user performs an action. However, unlike working with Ajax, Flex is independent of browser

implementations such as JavaScript or CSS. The framework runs on Adobe's cross-platform Flash Player.

Flex applications consist of many MXML and ActionScript files. They are compiled into a single SWF movie file which can be played by the Flash player installed on the client's browser.

**Note:** For Flex applications working with SOAP data, use the **Web Services** Vuser protocol.

## Flex Technologies

The following tables describe the specific technologies that are supported by the VuGen recording engine.

Technology	Description
AMF0	Action Message Format
AMF3	Action Message Format - Compressed format
RTMP	Real Time Message Protocol: Messaging and streaming over TCP
RTMPS	Real Time Message Protocol: Messaging and streaming over TCP/SSL
RTMPT	Real Time Message Protocol Tunneled: Messaging and streaming over HTTP

VuGen supports the following development solutions:

Development Platforms	Description
BlazeDS	Open Source Remoting and Messaging solution
GraniteDS	Open source development and integration solution for building Flex applications.
LiveCycle	Adobe development and integration solution for building Flex applications.

The table below displays a list of the LoadRunner documentation that relates to the process of developing a Flex Vuser script.

Topic	Description
Creating a Flex Vuser script	See VuGen's generic documentation about creating Vuser scripts [ <a href="#">"Creating Vuser Scripts - Overview" on page 162</a> ].

Topic	Description
Recording	<p>In addition to the generic documentation about recording Vuser scripts [<a href="#">"Recording - Overview" on page 174</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"How to Record a Flex Script" on page 639</a></li> <li>• <a href="#">"Setting the Flex Recording Mode" on page 640</a></li> <li>• <a href="#">"RTMP/RTMPT Streaming" on page 630</a></li> <li>• <a href="#">"RTMP Tunneled" on page 638</a></li> </ul> <p>You may need to configure recording options for your Flex script:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Flex &gt; RTMP Node" on page 197</a></li> <li>• <a href="#">"Flex &gt; Externalizable Objects Node (Recording)" on page 214</a></li> </ul>
Correlating	<p>In addition to the generic VuGen documentation on correlating Vuser scripts [<a href="#">"Correlation Overview" on page 274</a>], see:</p> <p><a href="#">"Flex Correlations" on page 643</a></p>
Replaying	<p>In addition to the generic VuGen documentation about replaying Vuser scripts [<a href="#">"Replaying - Overview" on page 316</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"How to Query an XML Tree" on page 646</a></li> </ul> <p>You may need to configure run-time settings for your Flex script:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Flex &gt; RTMP Node" on page 333</a></li> <li>• <a href="#">"Flex &gt; Externalizable Node (Run-Time Settings)" on page 334</a></li> <li>• <a href="#">"Flex &gt; Configuration Node (Run-Time Settings)" on page 332</a></li> </ul>
Debugging	<p>See the generic documentation about debugging Vuser scripts [<a href="#">"Debugging - Overview" on page 388</a>].</p> <ul style="list-style-type: none"> <li>• <a href="#">"Externalizable Objects in Flex Scripts" on page 642</a></li> <li>• <a href="#">"How to Serialize Flex Scripts " on page 645</a></li> </ul>
Viewing Test Results	<p>See the generic documentation about viewing test results [<a href="#">"Viewing Replay Results - Overview" on page 480</a>].</p>

## Recording Flex Scripts

When you record a Flex application, VuGen generates Flex Vuser script functions that emulate the application. The following tables describe the functions that are supported by the Flex protocol.

## AMF

VuGen's **Flex** protocol lets you create scripts that emulate Flex applications working with AMF0 and AMF3.

Function Name	Description
<b>flex_amf_call</b>	Sends an AMF request.
<b>flex_amf_define_envelope_header_set</b>	Defines a set of envelope headers.
<b>flex_amf_define_header_set</b>	Defines a set of AMF headers.
<b>flex_login</b>	Logs on to a password-protected Flex application.
<b>flex_logout</b>	Logs off of a password-protected Flex application.
<b>flex_ping</b>	Checks if a Flex application is available.
<b>flex_remoting_call</b>	Invokes one or more methods of a server-side Remote object (RPC).

### AMF Example 1:

In the following example, **flex\_ping** checks for the availability of a service. The **flex\_remoting\_call** function invokes the service remotely.

```
flex_ping("1",
    "URL=http://<HOST>/weborb.aspx",
    "Snapshot=t6.inf",
    LAST);
flex_remoting_call("getProductEdition::GenericDestination",
    "URL=http://testlab1/weborb30/console/weborb.aspx",
    "Snapshot=t1.inf",
    INVOCATION,
    "Target=/2",
    "Operation=getProductEdition",
    "Destination=GenericDestination",
    "DSEndpoint=my-amf",
    "Source=Weborb.Management.LicenseService",
    "Argument=<arguments/>",
    LAST);
```

### AMF Example 2:

In the following AMF0 example, the **flex\_amf\_call** function accesses a gateway and sends message to the server.

```
flex_amf_call("EchoAny",
    "Gateway=http://<host>/gateway.aspx",
```

```

"Snapshot=t1.inf",
"IsParseResponse=No",
MESSAGE,
"Method=EchoAMF.EchoAMF.EchoAny",
"TargetObjectId=/1",
BEGIN_ARGUMENTS,
    "<boolean>true</boolean>",
END_ARGUMENTS,
LAST);

```

#### AMF Example 3:

In the following AMF3 example, the **flex\_remoting\_call** function sends the server an AMF call that can be serialized.

```

flex_remoting_call(
"product::getProductsByName",
URL=http://<HOST>:<PORT>/amf;jsessionid={CorrelationParameter}",
"Snapshot=t1.inf",
"IsParseResponse=No",
INVOCATION,
"Target=/2",
"Operation=getProductsByName",
"Destination=product",
"DSEndpoint=my-amf",
"DSId=8E3759E5-E51A-3906-0EAB-6119CD1E26BF",
"Argument="
    "<arguments>"
        "<string>A</string>"
    "</arguments>",
LAST);

```

## RTMP Functions

Function Name	Description
<b>flex_rtmp_connect</b>	Connects a client to an RTMP server and sets connection options.
<b>flex_rtmp_disconnect</b>	Disconnects a client from an RTMP server.
<b>flex_rtmp_receive_stream</b>	Receives streaming data from an RTMP server.
<b>flex_rtmp_receive</b>	Receives responses from an RTMP server.
<b>flex_rtmp_send</b>	Sends a request to an RTMP server.

#### RTMP Example

In the following example, **flex\_rtmp\_receive** receives data.

```

flex_rtmp_receive("recv_step0",
"ConnectionID=19",
"Snapshot=tRTMP44.inf",
CHANNEL,
"ChunkStreamID=2",
CHANNEL,
"ChunkStreamID=2",
LAST);

```

## **RTMP Tunneled Functions**

Function Name	Description
<b>flex_rtmp_tunneled_connect</b>	Connects a client to an RTMP server over HTTP.
<b>flex_rtmp_tunneled_disconnect</b>	Disconnects a client from session over HTTP with an RTMP server.
<b>flex_rtmp_tunneled_send</b>	Sends a request to an RTMP server over HTTP.

### RTMP Tunneled Example

In the following example, **flex\_rtmp\_tunneled\_send** sends an RTMP tunneled request.

```

flex_rtmp_tunneled_send(
"send_step0",
"SessionID=0",
"Snapshot=t30.inf",
MESSAGE,
"DataType=command message amf3",
"ChunkStreamID=3",
"MessageStreamID=0",
"Argument="
    "<arguments>"
        ...
    "</arguments>",
LAST);

```

For detailed syntax information about all of the Flex functions, see the Function Reference ([Help > Function Reference](#)).

## **RTMP/RTMPT Streaming**

LoadRunner's Flex protocol supports recording and replay of streaming for both the RTMP and RTMPT protocols. You can record using either the regular recording mode or the simplified recording mode. The simplified mode enables VuGen to generate a single function in place of the

multiple functions that are generated when the regular recording mode is used. When you use the simplified mode to record, the following occurs:

- For an RTMP-based stream: VuGen generates a single **flex\_rtmp\_receive\_stream** step in place of many **flex\_rtmp\_receive** and **flex\_rtmp\_send** steps.
- For an RTMPT-based stream: VuGen generates a single modified **flex\_rtmp\_tunneled\_send** step in place of many **flex\_rtmp\_tunneled\_send** steps.

The single generated **flex\_rtmp\_receive\_stream** or **flex\_rtmp\_tunneled\_send** step makes the Vuser script more readable (by eliminating multiple lines of code), and makes the script replay more reliable. It is recommended that you use the simplified mode for recording your Vuser scripts, unless the Vuser activity includes asynchronous behavior, as described below.

The simplified recording mode is the default recording mode for streaming. To activate the simplified mode, open the **Recording Options** dialog box, click **Flex > RTMP**, and select the **Generate single step for RTMP/T stream handling** check box.

The differences between the simplified and regular recording modes are listed below:

	<b>Simplified mode</b>	<b>Regular mode</b>
(Recording option) Generate single step for RTMP/T stream handling check box	Selected	Not selected
Functions generated	RTMP: Generates <b>flex_rtmp_receive_stream</b> functions.  RTMPT: Generates <b>flex_rtmp_tunneled_send</b> functions.	Generates <b>flex_rtmp_receive</b> and <b>flex_rtmp_send</b> steps.
Number of functions generated per stream	One	Multiple
Supports asynchronous behavior	No	Yes
Default Mode	Yes	No

**Note:** The simplified recording mode is supported for Flash Media Server versions 3.5 and 4.

## Synchronous Vuser behavior

The **flex\_rtmp\_receive\_stream** and **flex\_rtmp\_tunneled\_send** functions that are generated when the simplified recording mode is selected are synchronous functions. This means that no other Vuser functions can be executed while either of these functions is executing. For example, consider a Vuser script that includes a **flex\_rtmp\_receive\_stream** function that streams a video for 5 minutes. During the 5 minute period during which the video is streaming, the Vuser will not be able to perform any other actions, such as clicking the **Pause** button or skipping to a different location in the video. Clicking a button while a video is streaming is an example of asynchronous behavior.

Although a single generated step makes script replay more reliable, it is not able to replay asynchronous actions (such as pause and seek) that you may have performed while recording the script. The single generated step also does not replay the automatic requests that the client performs when Dynamic Stream is in use. If it is important to replay these asynchronous actions, you must record the Vuser script using the regular recording mode - not the simplified recording mode - and then manually modify the generated script as described below.

#### Modifying scripts to replay asynchronous user actions

If your Vuser script must be able to replay asynchronous actions that are performed while a streaming action is executed, you must record the Vuser script using the regular recording mode - not the simplified recording mode - and then manually modify the generated script. The modified script will include a combination of single streaming steps and the more verbose steps that are generated with regular recording.

**Note:** In this section, we will use the term *required user actions* to refer to the actions that must be performed while a video is streamed.

To create a script that can replay asynchronous behavior, first you record the script using the regular recording mode - not the simplified recording mode. Thereafter, identify the **flex\_rtmp\_send** steps that represent *required user actions*. Then replace the steps between the *required user actions* with single streaming functions. See the sections below for details.

**Note:** The modification procedure differs slightly between RTMP and RTMPT steps.

#### Modifying recorded Flex RTMP steps

When you use the regular recording mode, VuGen generates **flex\_rtmp\_receive** and **flex\_rtmp\_send** steps for all communication with the server. This ensures that user actions such as pause and seek, as well as automatic requests that the client performs when Dynamic Stream is in use, are included in the script. However, this method also captures less-necessary lines of code that are difficult to read and may not be reliable during replay of streaming actions.

**Note:** To activate the regular recording mode, clear the **Generate single step for RTMP/T stream handling** check box in the **Flex > RTMP** pane of the Recording Options dialog box.

Follow the instructions below to remove the unnecessary **flex\_rtmp\_receive** and **flex\_rtmp\_send** steps from your script.

1. Search for the **flex\_rtmp\_send** step that contains the initial play argument. For example:

```
flex_rtmp_send("send_step2",
"ConnectionID=10",
"Snapshot=tRTMP6.inf",
MESSAGE,
```

```
...
...
MESSAGE,
...
...
"Argument=<arguments><string>play</string><number>0</number><null/>"  

...
LAST);
```

2. Delete or comment out the **flex\_rtmp\_receive** steps that occur during streaming. For example:

```
//this is the start of the stream:  

//      flex_rtmp_receive("recv_step2",  

//                          "ConnectionID=10",  

//                          "Snapshot=tRTMP7.inf",  

//                          CHANNEL,  

//                          "ChunkStreamID=2",  

//                          CHANNEL,  

//                          "ChunkStreamID=2",  

//                          CHANNEL,  

//                          "ChunkStreamID=4",  

//                          CHANNEL,  

//                          "ChunkStreamID=2",  

//                          LAST);  

//  

//      flex_rtmp_receive("recv_step3",  

//                        "ConnectionID=10",  

//                        "Snapshot=tRTMP8.inf",  

//                        CHANNEL,
```

```

//           "ChunkStreamID=5",

//           CHANNEL,

//           ...

//           ...

```

3. Remove the **flex\_rtmp\_send** steps that are not related to the required user actions, such as "user control message" types. For example:

```

//     flex_rtmp_send("send_step3",
//                   "ConnectionID=10",
//                   "Snapshot=tRTMP9.inf",
//                   MESSAGE,
//                   "DataType=user control message",
//                   "EventType=set buffer length",
//                   "MessageStreamID=1",
//                   "BufferLength=100",
//                   LAST);

```

4. When you find a **flex\_rtmp\_send** step that represents a required user action, do the following:

- a. Manually add a **flex\_rtmp\_receive\_stream** step before the send step.
  - Make sure that the **ConnectionID** argument has the same value as the steps you removed above it.
  - The **Snapshot** argument is not relevant for the manually added step.
  - You can use the **ContinueToNextStepAfter = <msec>** argument to control the minimum play duration of the stream to download before continuing to the next step.
- b. Determine the **flex\_rtmp\_send** steps that represent the required user actions. These will likely include arguments such as **pauseRaw**, **pause**, **seek** and **play2** (for Dynamic Stream). For example:

```

flex_rtmp_send("send_step5",
               "ConnectionID=10",
               "Snapshot=tRTMP62.inf",
               MESSAGE,

```

```

"DataType=command message amf3",
"ChunkStreamID=8",
"MessageStreamID=1",
"Argument=<arguments><string>pauseRaw</string><number>0</number><null/>""
"<boolean>true</boolean><number>12000</number></arguments>",
LAST);

```

- c. Determine whether there are some extra **flex\_rtmp\_send** steps that you can remove. For example, if you dragged a button to seek in the stream, subtle jerks in the motion may be recorded as separate pause and seek actions. In these cases, may not need all of them. Keep only those that describe the desired operations.
- d. Identify the **flex\_rtmp\_receive** step that indicates that the server has received the end of the user action. For example:

```

//this is the confirmation from the server on the "seek" command.

flex_rtmp_receive("recv_step55",
"ConnectionID=10",
"Snapshot=tRTMP68.inf",
CHANNEL,
"ChunkStreamID=2",
CHANNEL,
"ChunkStreamID=2",
LAST);

```

- 5. Repeat steps 2 - 4 for each set of unnecessary receive data and required user actions in your script.

For additional details on **flex\_rtmp\_receive\_stream** including a complete example, see the Function Reference ([Help > Function Reference](#)).

### Modifying recorded Flex RTMPT steps

When you use the regular recording mode, VuGen generates a **flex\_rtmp\_tunneled\_send** step for all communication with the server. This ensures that user actions such as pause and seek, as well as automatic requests that the client performs when Dynamic Stream is in use, are included in the script. However, this method also captures less-necessary lines of code that are difficult to read and may not be reliable during replay of streaming actions.

**Note:** To activate the regular recording mode, clear the **Generate single step for**

**RTMP/T stream handling** check box in the **Flex > RTMP** pane of the Recording Options dialog box.

Follow the instructions below to remove the unnecessary steps from your script.

1. Search for the **flex\_rtmp\_tunneled\_send** step that contains the initial play argument. For example:

```
flex_rtmp_tunneled_send("send_step2",
    "SessionID=1",
    "Snapshot=t36.inf",
    MESSAGE,
    ...
    ...
    MESSAGE,
    ...
    ...
    "Argument=<arguments><string>play</string><number>0</number><null/>"  
...
LAST);
```

2. Remove **flex\_rtmp\_tunneled\_send** steps that are not related to required user actions, such as "user control message" types. For example:

```
//      flex_rtmp_tunneled_send("send_step3",
//          "SessionID=10",
//          "Snapshot=t15.inf",
//          MESSAGE,
//          "DataType=user control message",
//          "EventType=set buffer length",
//          "MessageStreamID=1",
//          "BufferLength=100",
//          LAST);
```

3. When you find a **flex\_rtmp\_tunneled\_send** step that represents a required user action, do the following:

- a. Add a **ContinueToNextStepAfter = <msec>** argument to the previous step. The **ContinueToNextStepAfter = <msec>** argument controls the minimum play duration of the stream to download before continuing to the next step. For example:

```
flex_rtmp_tunneled_send("send_step2",
```

```

"SessionID=1",
"Snapshot=t36.inf",

//Read the stream until at least 15 seconds of media have been downloaded
"ContinueToNextStepAfter = 15000",
MESSAGE,
...
...
MESSAGE,
...
...
"Argument=<arguments><string>play</string><number>0</number><null/>"

...
LAST);

```

- b. Determine the **flex\_rtmp\_tunneled\_send** steps that represent the required user actions. These will typically include arguments such as **pauseRaw**, **pause**, **seek** and **play2** (for Dynamic Stream). For example:

```

flex_rtmp_tunneled_send("send_step5",
"SessionID=10",
"Snapshot=t16.inf",
MESSAGE,
"DataType=command message amf3",
"ChunkStreamID=8",
"MessageStreamID=1",
"Argument=<arguments><string>pauseRaw</string><number>0</number><null/>"<boolean>true</boolean><number>12000</number></arguments>",
LAST);

```

- c. Determine whether there are extra **flex\_rtmp\_tunneled\_send** steps that you can remove. For example, if you dragged a button to seek in the stream, subtle jerks in the motion may be recorded as separate pause and seek actions. In these cases, you may not need all of them. Keep only those that describe the desired operations.

4. Repeat steps 2 - 3 for each set of unnecessary send data and required user actions in your script.

For additional details on the **flex\_rtmp\_tunneled\_send** function, including a complete example, see the Function Reference ([Help > Function Reference](#)).

## Live Streaming

VuGen's Flex protocol supports Adobe's Live Streaming. If VuGen detects a live stream while you record a Vuser script, VuGen adds '**ContinueToNextStepAfter**' and '**ContinueMode**' arguments to the generated **flex\_rtmp\_receive\_stream** or **flex\_rtmp\_tunneled\_send** function. These additional arguments enable the live stream to be accurately replayed. For details on these arguments, see the Function Reference ([Help > Function Reference](#)).

**Note:** The default value of the generated **ContinueToNextStepAfter** argument is the length of time (in milliseconds) for which the video was streamed while the Vuser script was recorded.

## RTMP Tunneled

VuGen supports the recording of RTMP Tunneled steps in Flex application which are split into the following step types:

- **Messaging support.** The Flex protocol supports enhanced record and replay of messaging and has been verified for Adobe LiveCycle Data Services ES2 Version 3.1.
- **Streaming support.** The Flex protocol supports enhanced record and replay of streaming. For details, see "[RTMP/RTMPT Streaming](#)" on page 630.

When you record a Flex stream, by default, LoadRunner generates a single **flex\_rtmp\_tunneled\_send** step in place of many **flex\_rtmp\_tunneled\_send** steps. The **flex\_rtmp\_tunneled\_send** step makes your script more readable (eliminating tens or hundreds of lines) and makes the replay more reliable.

**Note:** The new **flex\_rtmp\_tunneled\_send** step is generated when the **Generate single RTMP/T step** option is selected in the **Flex:RTMP** pane of the **Recording Options** dialog box. Although this step makes the script more reliable, it does not replay certain actions you may perform while recording your script, such as pause and seek. It also does not replay the automatic requests that the client performs when Dynamic Stream is in use.

If it is important to replay these actions, you can clear the **Generate single RTMP/T step** option in the **Flex > RTMP** pane of the **Recording Options** dialog box, which causes LoadRunner to generate the steps for all of the raw streaming data.

However, to ensure proper replay, you must manually modify the generated script as described in "[RTMP/RTMPT Streaming](#)" on page 630.

The above functionality has been verified for Flash Media Server versions 3.5 and 4.

- **Externalizable objects.** LoadRunner supports externalizable objects over RTMP Tunneled. For details, see "[Externalizable Objects in Flex Scripts](#)" on page 642.

- **User Data Points.** LoadRunner generates a number of new data points that provide more useful information for analysis.
- The Flex RTMP-Tunneled protocol supports manual correlation using `web_reg_save_param_xpath API`.

For additional details on `flex_rtmp_tunneled_send` including a complete example, see the Function Reference ([Help > Function Reference](#)).

## How to Record a Flex Script

This task describes how to record a script using the Flex Vuser protocol.

### Create a new script or open an existing script

Select **New Script and Solution > Flex protocol**

For details, see "[How to Create or Open a Vuser Script](#)" on page 162.

### Configure the recording options

The recording options contain options that affect the way that a Vuser script is generated after recording or regenerating the script.

In a Flex script, you will need to configure the following recording options:

- **Recording options > Flex > RTMP > Generate single step for RTMPT/Streaming**

This option, selected by default, enables VuGen to create a single step while recording a stream. However, when you create a single step, certain actions are not replayed, such as pause and seek. If you want to be able to replay these actions, disable the option.

- **Recording Options > Flex > Configuration > Use External JVM**

If you are using an external Java Virtual Machine select this option and configure the path of the JVM in the value field.

- **Recording Options > Flex > Configuration > Use GraniteDS**

Check this option if you are using GraniteDS as a sever side Data Service configuration.

- **Recording Options > Flex > Externalizable Objects**

This option enables you to specify additional .jars that are required to record your script.

For details, see "[Externalizable Objects in Flex Scripts](#)" on page 642.

For concept and user interface details, see "[Recording Options](#)" on page 176.

### Initialize the recording session

When creating a new script, this occurs automatically. To manually start recording, click the **Start Record** button on the VuGen toolbar, complete the Start Recording dialog box, and then click **Start**.

**Recording.** VuGen's floating toolbar appears, VuGen opens your application and begins recording your actions.

- For user interface details, see "[Start Recording Dialog Box](#)" on page 266.
- For details on the script sections into which you can record, see "[Vuser Script Sections](#)" on page 255.

## Perform business processes on your application

Perform the desired business processes that you wish to record. The floating toolbar allows you to insert transactions, rendezvous points, and comments. You can also use the floating toolbar to specify into which section of the script to record. For user interface details, see "[Floating Recording Toolbar](#)" on page 269.

Click the **Stop** button  on the floating toolbar when you are finished recording.

Regenerate the code

After recording, regenerate the script to determine if all the steps have been correctly parsed.

For details, see "[Code Generation in the Flex Protocol](#)" on the next page.

## Setting the Flex Recording Mode

You can instruct VuGen how to generate a script from a Flash Remoting session using the Flex and Web Protocols.

### Example

Use Web HTTP technology to generate **web\_custom\_request** functions with the Flash Remoting information.

```
web_url("flash",
    "URL=http://<HOST>:<PORT>/flash/",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t1.inf",
    "Mode=HTML",
    EXTRARES,
    "Url=movies/XMLExample.swf", "Referer=", ENDITEM,
    "Url=movies/JavaBeanExample.swf", "Referer=", ENDITEM,
    LAST);
web_link("Sample JavaBean Movie Source",
    "Text=Sample JavaBean Movie Source",
    "Snapshot=t2.inf",
    EXTRARES,
    "Url=XMLEExample.swf", "Referer=", ENDITEM,
```

```

    "Url=JavaBeanExample.swf", "Referer=", ENDITEM,
    LAST);
web_custom_request("gateway",
    "URL=http://<HOST>:<PORT>/flashservices/gateway",
    "Method=POST",
    "Resource=0",
    "RecContentType=application/x-amf",
    "Referer=",
    "Snapshot=t3.inf",
    "Mode=HTML",
    "EncType=application/x-amf",
    "BodyBinary=\x00\x00\x00\x01\x00\x10amf_server_debug\x01
        \x00\x00\x00`\'\x03\x00\ncoldfusion\x01\x01\x00
        namfheaders\x01\x00\x00\x03amf\x01\x00\x00
        \x0Bhttpheaders\x01\x00\x00\trecordset\x01\x01
        \x00\x05error\x01\x01\x00\x05trace\x01\x01
        \x00\x07m_debug\x01\x01\x00\x00\t\x00\x01
        \x00/flashgateway.samples.FlashJavaBean.testDocument
        \x00\x02/1\x00\x00\x004\n\x00\x00\x00\x01
        \x0F\x00\x00\x00*<TEST message=\"test\"><INSIDETEST /></TES
T>",
    LAST);

```

## Code Generation in the Flex Protocol

### Code Generation Notification

If a Flex, Silverlight, or Java over HTTP script encounters an error during the code generation phase, VuGen issues a warning. This warning appears in the Errors pane, when the **Warnings** button is selected, and the **Define Available Categories** filter is set to **All** or **Code Generation Notification**. The list of warnings displays details about each error, as well as recommended actions for resolving the problem. Follow the recommended actions and regenerate the script.

If the error is related to externalizable objects in a Flex script, see "[Externalizable Objects in Flex Scripts](#)" on the next page.

To manually open the Errors pane at any time, select **View > Errors**.

### Parsing Responses in Flex Scripts

When generating a Flex script, LoadRunner attempts to parse responses for any of the following steps:

- flex\_amf\_call
- flex\_remoting\_call
- flex\_login
- flex\_logout
- flex\_ping

If the parsing fails, the following attribute is dynamically added to the step:

```
IsParseResponse = No
```

This instructs LoadRunner not to parse the responses for that step during script replay. Every time you regenerate the script, LoadRunner will attempt to parse again, and will set this parameter to false if it fails. If needed, you can delete this line, or set the value to = 'Yes' to force LoadRunner to parse responses for that step during replay.

Additionally, you can manually add the attribute and set the value to 'No' in a generated script, even if the parse is successful, as it may enhance replay performance.

## Externalizable Objects in Flex Scripts

When recording a Flex application, information is usually passed between the client and server using known serialization methods (AMF). If this is the case, VuGen creates a `flex_amf_call` and both the request and response are parsed.


However, when a given AMF object uses a custom serialization method (externalizable), VuGen automatically issues a warning. This warning displays details about the exception, as well as recommended actions for resolving it.

The following are some examples of the exceptions that the generated script may include when an AMF object uses a custom serialization method:

- **Request and response not parsed.** This exception is automatically displayed in the Errors pane when the **Warnings** button is selected, and the **Define Available Categories** filter is set to **All** or **Code Generation Notification**. Details about the exception are listed, as well as recommended actions. For details, see "[Errors Pane](#)" on page 133.
- **Request parsed but response is not parsed.** VuGen generates a `IsParseResponse=No` statement. Additionally, VuGen issues a warning that is automatically displayed in the Errors pane when the **Warnings** button is selected, and the **Define Available Categories** filter is set to **All** or **Code Generation Notification**. The list of warnings displays details about the exception, as well as recommended actions. For details, see "[Errors Pane](#)" on page 133.

For details on configuring the **Recording Options > Flex > Externalizable Objects** Node, see "[Flex > Externalizable Objects Node \(Recording\)](#)" on page 214.

The following flowchart illustrates the steps to resolve externalizable objects in Flex scripts:



For details on how to serialize externalizable objects, see:

- ["Flex > Externalizable Objects Node \(Recording\)" on page 214](#)
- ["How to Serialize Flex Scripts " on page 645](#)

## Flex Correlations

VuGen supports correlation in Flex scripts.

Support for correlations applies to the following Flex steps:

- flex\_login
- flex\_logout
- flex\_ping
- flex\_amf\_call
- flex\_remoting\_call
- flex\_rtmp\_tunneled\_connect
- flex\_rtmp\_tunneled\_send

Flex correlation includes integration with the following features:

- **Correlations rules**

**DSid, jsessionid, and RTMPT ID**

- **Design Studio**
- **Manual correlation** using the API `web_reg_save_param_xpath`.

For general information, see "[Correlation Tab \[Design Studio\] Overview](#)" on page 275.

For task details, see "[How to Correlate Scripts Using Design Studio](#)" on page 280.

## Flex Snapshots

Vuser scripts based on the Flex protocol utilize VuGen's Snapshot pane.

- For an introduction to the Snapshot pane, see "[Snapshot Pane - Overview](#)" on page 85.
- For details on how to work with the Snapshot pane, see "[How to Work with Snapshots](#)" on page 88.
- For details on the Snapshot pane UI, see "[Snapshot Pane](#)" on page 126.

In addition, a new snapshot has been designed to show Flex data in several views:

- Raw Data

The data received from the server that has not been formatted or parsed in any way.

- Response Body

Data entity received from the server


- Request Body

Data entity sent to the server

- Headers

If the Response Body and the Request Body are in XML format, the data can be displayed as:

- Text
- Hex
- XML



## How to Serialize Flex Scripts

### Serialize Using External Java Serializer

You can use the Java classes from the Flex server to serialize AMF messages in your script. This process has been simplified so that you need to include the application JAR files only if the AMF objects implement an externalizable interface.

1. In the **Recording Options > Flex > Externalizable Objects** node, select **Serialize objects using** and select **Custom Java Classes** from the drop-down menu.
2. Add the relevant files by using the **Add all classes in folder** or **Add JAR or Zip file** buttons. Add the following files:
  - a. For **Adobe BlazeDS or Adobe LCDS**, add the following JAR files:
    - flex-messaging-common.jar
    - flex-messaging-core.jar

- b. Regenerate the script and note any errors. Open the recording options dialog box using the **Generation Options** button and add the necessary application JAR files.
3. Ensure that the added files exist in the same location both on the VuGen machine and on all load generators.

For details, see "[Externalizable Objects in Flex Scripts](#)" on page 642.

### Notes and Limitations for the Java Serializer

- Supported JDK versions: 1.6 and earlier.
- Supported servers: Adobe BlazeDS and Adobe Livecycle DS.
- Microsoft .NET classes are not supported.
- During code generation VuGen performs a validity test of the request buffers by verifying that the buffer can be read and written using the provided jars. Failure in this validity test indicates that the classes are incompatible with LoadRunner.

### Use the LoadRunner Serializer

You can attempt to serialize externalizable objects using the LoadRunner serializer. Ensure that you have saved all open scripts because this option may result in unexpected errors or invalid steps.

1. Save all open scripts in VuGen.
2. In the **Recording Options > Flex > Externalizable Objects** node, select **Serialize objects using** and select **LoadRunner AMF serializer** from the Reference


## How to Query an XML Tree

VuGen provides a Query Builder that lets you create and execute queries on the XML.


VuGen displays the XML code in an expandable tree. You can perform a query on your XML document, and search for a specific Namespace URI, value, or attribute. Note that all queries are case-sensitive.

### Perform a query

1. In the Snapshot pane, select the node that you want to search. Click the **Find XML** button. The Find XML dialog button opens.




2. Select **Request** or **Response**. Enter an XPath query and click **OK**. To formulate a query, click **Query Builder...** button. The XML Node Query dialog box opens.
3. Enable one or more items for searching.




4. Enable the **Name** section to search for the name of a node or element.
5. Enable the **Namespace URI** section to search for a namespace.
6. Enable the **Text** section to search for the value of the element indicated in the Name box.

7. Enable the **Attributes** section to search for an attribute.
8. Enter the search text in the appropriate boxes. To add an attribute, click the **Add** button. The Attribute Properties box opens. Enter an attribute name and value. Click **OK**.



9. Click **OK** in the XML Node Query dialog box. VuGen places the text of the query in the Find XML box.



10. Click **Find Next** to begin the search.

## Flex - Troubleshooting and Limitations

This section describes troubleshooting and limitations for the Flex Protocol.

- A Flex script cannot be generated using an external Java Virtual Machine (JVM) version 1.4 or lower.
- If your script contains more than one **flex\_RTMP\_tunneled\_connect** step, with the same gateway parameter, you must insert a disconnect step for the previous **flex\_RTMP\_tunneled\_connect** step before you connect again. For example:

```
Flex_rtmp_tunneled_connect("connect_step0",
"SessionId=0",
"Gateway=http://123.123.123.123:1935",
.

LAST);

.

Flex_rtmp_tunneled_disconnect("disconnect_step0",
"SessionId=0")
flex_rtmp_tunneled_connect("connect_step1",
"SessionId=1",
"Gateway=http://123.123.123.123:1935",
.

LAST);

.

Flex_rtmp_tunneled_disconnect("disconnect_step0",
"SessionId=1")
```

- If a subsequent **flex\_rtmp\_tunneled\_connect** command has the same gateway parameter as the previous **flex\_rtmp\_tunneled\_connect** step and the **flex\_rtmp\_tunneled\_disconnect** step is omitted, the script will pause indefinitely.

## GraniteDS (Data Services)

- If you have modified the granite-config.xml, copy it to the <LoadRunnerInstallation>\dat directory.
- When switching between BlazeDS and GraniteDS parsing (**Recording Options > Flex > Configuration**), VuGen must be restarted.
- LoadRunner cannot serialize both GraniteDS and BlazeDS/LCDS messages in the same script.
- Flex RTMP messaging support. All limitations that apply to AMF3 parsing apply to externalizable objects over RTMP.
- **flex\_rtmp\_receive\_stream** step. If the Generate **flex\_rtmp\_receive\_stream** step option is

enabled, all transactions, comments, and rendezvous points that you add from the Recording toolbar are added to the script after the **flex\_rtmp\_receive\_stream** step in your script.

- Web diagnostics does not work for RTMP and RTMPT steps (even when the breakdown is enabled).
- You cannot replay two RTMPT steps at once.

## Java Protocols

### Java Protocol Recording Overview

Using VuGen, you can record a Java application or applet. VuGen creates a pure Java script enhanced with Vuser API Java-specific functions. After recording, you can enhance or modify the script with standard Java code using JDK libraries or custom classes.

After you prepare your script, you run it in standalone mode from VuGen. Sun's standard Java compiler, **javac.exe**, checks the script for errors and compiles it. Once you verify that the script is functional, you incorporate it into a LoadRunner scenario or Business Process Monitor configuration.

When you create a script through recording and manual enhancements, all of the guidelines and limitations associated with Java Vuser scripts apply. In addition, any specific classes used in the script must be present on the machine executing the Vusers and indicated by the **classpath** environment variable. See "[Java Vuser Protocol - Manually Programming Scripts](#)" on page 667 for important information about function syntax and system configuration.

Before recording a CORBA session, verify that your application or applet functions properly on the recording machine.

Make sure that you have properly installed a JDK version from Sun on the machine running VuGen—JRE alone is insufficient. You must complete this installation before recording a script. Verify that the **classpath** and **path** environment variables are set according to the JDK installation instructions.

**Note:** When you load an applet or application from VuGen during recording, it may take several seconds longer than if you were to load it independent of VuGen.

VuGen provides a tool that enables you to convert a Vuser script created for Web, into Java. For more information, see "[How to Convert a Web \(HTTP/HTML\) Vuser Script into a Java Vuser Script](#)" on page 812.

After recording, you can enhance or modify the script with standard Java code using JDK libraries or custom classes.

After you prepare your script, you run it in standalone mode from VuGen. Sun's standard Java compiler, **javac.exe**, checks the script for errors and compiles it.

You integrate finished scripts into your environment: a LoadRunner scenario, Performance Center load test, or Business Process Monitor configuration. For more information, see the Function Reference, or *Performance Center* documentation.

**Note:** By default, Java 7 enables the Java Split Verifier. This prevents Java recording in LoadRunner. LoadRunner uses the **-XX:-UseSplitVerifier** key while initializing the JVM during recording, to disable the verifier. This adaptation does not require any user intervention.

## Java Vuser Script Overview

When you record a session, VuGen logs all calls to the server and generates a script with functions. These functions describe all of your actions within the application or applet. The script also contains supplementary code required for proper playback, such as property settings, and naming service initialization (JNDI).

The recorded script is comprised of three sections:

- Imports
- Code
- Variables

The **Imports** section is at the beginning of the script. It contains a reference to all the packages required for compiling the script. The **Code** section contains the Actions class and the recorded code within the **init**, **actions**, and **end** methods. The **Variables** section, after the **end** method, contains all the type declarations for the variables used in the code.

After you finish recording, you can modify the functions in your script, or add additional Java or LoadRunner functions to enhance the script. Note that if you intend to run Java Vusers as threads, the Java code you add to your script must be thread-safe. For details about function syntax, see the Function Reference (**Help > Function Reference**). In addition, you can modify your script to enable it to run as part of another package. For more information, see "[Compiling and Running a Script as Part of a Package](#)" on page 670.

## RMI over IIOP Overview

The **Internet Inter-ORB Protocol** (IIOP) technology was developed to allow implementation of CORBA solutions over the World Wide Web. IIOP lets browsers and servers exchange complex objects such as arrays, unlike HTTP, which only supports transmission of text.

**RMI over IIOP** technology makes it possible for a single client to access services which were only accessible from either RMI or CORBA clients in the past. This technology is a hybrid of the JRMP protocol used with RMI and IIOP used with CORBA. **RMI over IIOP** allows CORBA clients to access new technologies such as **Enterprise Java Beans** (EJB) among other J2EE standards.

VuGen provides full support for recording and replaying Vusers using the **RMI over IIOP** protocol. Depending on what you are recording, you can utilize VuGen's RMI recorder to create a script that will optimally emulate a real user:

- **Pure RMI client.** recording a client that uses native JRMP protocol for remote invocations
- **RMI over IIOP client.** recording a client application that was compiled using the IIOP protocol instead of JRMP (for compatibility with CORBA servers).

## Corba Recording Options

For recording a CORBA session, you need to set the following options in the Recording Options:

- JNDI
- Use DLL hooking to attach VuGen support

## CORBA Application Vendor Classes

Running CORBA applications with JDK1.2 or later, might load the JDK internal CORBA classes instead of the specific vendor CORBA classes. To force the virtual machine to use the vendor classes, specify the following java.exe command-line parameters:

### **Visigenic 3.4**

```
-Dorg.omg.CORBA.ORBClass=com.visigenic.vbroker.orb.ORB
-Dorg.omg.CORBA.ORBSingletonClass=com.visigenic.vbroker.orb.
    ORBSingleton
```

### **Visigenic 4.0**

```
-Dorg.omg.CORBA.ORBClass=com.inprise.vbroker.orb.ORB
-Dorg.omg.CORBA.ORBSingletonClass=com.inprise.vbroker.orb.ORBSingleton
```

### **OrbixWeb 3.x**

```
-Dorg.omg.CORBA.ORBClass=IE.Iona.OrbixWeb.CORBA.ORB
-Dorg.omg.CORBA.ORBSingletonClass=IE.Iona.OrbixWeb.CORBA.
    singletonORB
```

### **OrbixWeb 2000**

```
-Dorg.omg.CORBA.ORBClass=com.iona.corba.art.artimpl.ORBIImpl
-Dorg.omg.CORBA.ORBSingletonClass=com.iona.corba.art.artimpl.
    ORBSingleton
```

## Recording RMI

Before recording an RMI session, verify that your application or applet functions properly on the recording machine.

Before you record, verify that your environment is configured properly. Make sure that the required classes are in the classpath and that you have a full installation of JDK. For more information on the required environment settings, see "["How to Manually Create a Java Script" on page 671](#)".

## Recording a Jacada Vuser

The Jacada Interface Server provides an interface layer for mainframe applications. This layer separates the user interface from the application logic in order to insulate the organization from

changes in standards and technologies. Instead of working with green-screen applications, the Jacada server converts the environment to a user friendly interface.

VuGen records Jacada's Java thin-client. To record communication with the Jacada server through the HTML thin-client, use the Web HTTP/HTML type Vuser. For more information, see ["Web Protocols \(Generic\)" on page 818](#).

Before replay, you must also download the **clbase.jar** file from the Jacada server. All classes used by the Java Vuser must be in the classpath—either set in the machine's classpath environment variable or in the **Classpath Entries** list in the **Classpath** node of the run-time settings.

During replay, the Jacada server may return screens from the legacy system, in a different order than they appear in the recorded script. This may cause an exception in the replay. For information on how to handle these exceptions, contact HP support.

## Working with CORBA

CORBA-specific scripts usually have a well-defined pattern. The first section contains the ORB initialization and configuration. The next section indicates the location of the CORBA objects. The following section consists of the server invocations on the CORBA objects. The final section includes a shutdown procedure which closes the ORB. Note that pattern is not mandatory and that each one of these sections may appear multiple times within a script.

In the following segment, the script initializes an ORB instance and performs a bind operation to obtain a CORBA object. Note how VuGen imports all of the necessary classes.

```
import org.omg.CORBA.*;
import org.omg.CORBA.ORB.*;
import lrapi.lr;
public class Actions {
    // Public function: init
    public int init() throws Throwable {
        // Initialize Orb instance...
        MApplet mapplet = new MApplet("http://chaos/classes/", null);
        orb = org.omg.CORBA.ORB.init(mapplet, null);

        // Bind to server...
        grid = grid_dsi.gridHelper.bind("gridDSI", "chaos");
        return lr.PASS;
    }
}
```

The `org.omg.CORBA.ORB` function makes the connection to ORB. Therefore, it should only be called once. When running multiple iterations, place this function in the **init** section.

In the following section, VuGen recorded the actions performed upon a grid CORBA object.

```
// Public function: action
public int action() throws Throwable {

    grid.width();
    grid.height();
    grid.set(2, 4, 10);
    grid.get(2, 4);
```

```

        return lr.PASS;
    }

At the end of the session, VuGen recorded the shutdown of the ORB. The variables used
throughout the entire recorded code appear after the end method and before the Actions class
closing curly bracket.

// Public function: end
public int end() throws Throwable {
    if (lr.get_vuser_id() == -1)
        orb.shutdown();
    return lr.PASS;
}

// Variable section
org.omg.CORBA.ORB orb;
grid_dsi.grid ;
}

```

Note that the ORB shutdown statement was customized for this product. This customization prevents a single Vuser's shutdown from shutting down all other Vusers.

## Working with RMI

This section describes the elements of the Java Vuser script that are specific to RMI. RMI does not have constructs (as in CORBA)—instead it uses Serializable Java objects. The first section performs a Naming Registry initialization and configuration. The next section is generated when Java objects (both Remote and Serializable) are located and casted. The following section consists of the server invocations on the Java objects. In RMI there is no specific shutdown section (unlike CORBA). Note that objects might appear multiple times within the script.

The following segment locates a naming registry. This is followed by a lookup operation to obtain a specific Java object. Once you obtain the object, you can work with it and perform invocations such as **set\_sum**, **increment**, and **get\_sum**. The following segment also shows how VuGen imports all of the necessary RMI classes.

```

Import java.rmi.*;
Import java.rmi.registry.*;
:
:
// Public function: action
public int action() throws Throwable {

    _registry = LocateRegistry.getRegistry("localhost",1099);
    counter = (Counter)_registry.lookup("Counter1");
    counter.set_sum(0);
    counter.increment();
    counter.increment();
    counter.get_sum();
    return lr.PASS;
}
:
```

When recording RMI Java, your script may contain several calls to **lr.deserialize**, which deserializes all of the relevant objects. The **lr.deserialize** calls are generated because the object being passed to the next invocation could not be correlated to a return value from any of the previous calls. VuGen therefore records its state and uses **lr.deserialize** call to represent these values during replay. The deserialization is done before VuGen passes the objects as parameters to invocations. For more information, see "[How to Correlate Scripts - Java Scripts - Serialization](#)" on page 296.

## Working with Jacada

The Actions method of a Java Vuser script using Jacada, has two main parts: properties and body. The properties section gets the server properties. VuGen then sets the system properties and connects to the Jacada server.

```
// Set system properties...
    _properties = new Properties(System.getProperties());
    _properties.put("com.ms.applet.enable.logging", "true");
    System.setProperties(_properties);

    _jacadavirtualuser = new cst.client.manager.JacadaVirtualUser();

    lr.think_time(4);
    _jacadavirtualuser.connectUsingPorts("localhost", 1100, "LOADTEST", "", "", "");
    ...
    ...


```

The body of the script contains the user actions along with the exception handling blocks for the **checkFieldValue** and **checkTableCell** methods.

```
1...
/*
try {
    _jacadavirtualuser.checkFieldValue(23, "S44452BA");
}catch(java.lang.Exception e) {
    lr.log_message(e.getMessage());
}
*/
1...
/*
try {
    _jacadavirtualuser.checkTableCell(41, 0, 0, "");
}catch(java.lang.Exception e) {
    lr.log_message(e.getMessage());
}
*/
1...
```

The **checkField** method has two arguments: field ID number and expected value. The **checkTableCell** method has four arguments: table ID, row, column, and expected value. If there is a mismatch between the expected value and the received value, an exception is generated.

By default, the try-catch wrapper blocks are commented out. To use them in your script, remove the comment markers.

In addition to the recorded script, you can add any of the Java Vuser API functions. For a list of these functions and information on how to add them to your script, see "[Java Vuser Protocol - Manually Programming Scripts](#)" on page 667.

## Java Custom Filters - Overview

This section describes the background information necessary to create custom Java filters. For task details, see "[How to Create a Custom Java Filter](#)" on page 663.

When testing your Java application, your goal is to determine how the server reacts to client requests. When load testing, you want to see how the server responds to a load of many users. With VuGen's Java Vuser, you create a script that emulates a client communicating with your server.

VuGen provides filter files that define hooking properties for commonly used methods. There are filter definitions for RMI, CORBA, JMS, and JACADA protocols. You can also define custom filters.

When you record a method, the methods which are called from the recorded method either directly or indirectly, will not be recorded.

In order to record a method, VuGen must recognize the object upon which the method is invoked, along with the method's arguments. VuGen recognizes an object if it is returned by another recorded method provided that:

- The construction method of that object is hooked.
- It is a primitive or a built-in object.
- It supports a serializable interface.

You can create a custom filter to exclude unwanted methods. When recording a Java application, your script may include calls to methods that do not affect the server, such as calls to a local utility or the GUI interface. These calls are usually not relevant to your testing goals, and it would be correct to filter them out.

The built-in filters for RMI, CORBA, JMS, and JACADA protocols were designed to record only the server related traffic relevant to your testing goals. In some instances, however, you may need to customize filters to capture your JAVA application's calls or exclude unnecessary calls. Custom JAVA protocols, proprietary enhancements and extensions to the default protocols, and data abstraction all require a custom filter definition.

Before creating a test, we recommend that you become familiar with your application and determine its primary classes and methods, so that you will know which ones to include in your recording.

If you are not familiar with your application's classes, VuGen allows you to record with a stack trace that logs all of the methods that were called by your application. In order to record with stack trace set the log level to **Detailed**.

## Java Custom Filters - Determining which Elements to Include

When designing a custom filter, we recommend that you start by choosing the appropriate built-in filter as a base filter. You can then customize the filter using one of the following approaches:

- **Top Down Approach.** An approach in which you include the relevant package and exclude specific classes that are not part of the client-server activity. This is recommended if you are familiar with your application and you can identify a well-defined layer which implements all client-server activity without involving any GUI elements.
- **Bottom up Approach.** An approach in which you use the default filter and refine it by adding individual methods or classes. Use this approach if you cannot identify a well-defined layer or if you are not familiar with your application. Do not add all AUT packages and then try to remove extra component one by one.

The following section provides guidelines on when to include or exclude elements.

- If, as a result of your including a class, your script has many unrelated method calls, try modifying the filter to exclude the irrelevant methods.
- If you identify a non-client/server call in your script, exclude its method in the filter.
- During recording, VuGen may detect an unknown input argument, for example, an argument whose construction it had never encountered before. If this argument supports serialization, VuGen serializes it by saving it to a file in a special format. During replay, VuGen reconstructs the argument by deserializing it.
- VuGen serializes objects passed as arguments that were not included by the filter. We recommend that you include this object in the filter in order to track its construction and activity instead of using it in its serialized form. You can identify serialized objects in the script by searching for calls to the `Ir.deserialize()` method in your script. For more information see "[How to Correlate Scripts - Java Scripts - Serialization](#)" on page 296.
- Exclude all activity which involves GUI elements.
- Add classes for utilities that may be required for the script to be compiled.

## How to Record a Java Vuser Script

This task describes how to record a Java Vuser script.

It is important to note here that Java protocols can only record 32-bit applications, therefore 32bit executable should be used.

Also user can specify directly a .bat file to be recorded.

## 1. Prerequisites

Make sure that you have properly installed a JDK version from Sun on the machine running the Vusers—JRE alone is insufficient. Verify that the classpath and path environment variables are set according to the JDK installation instructions. Before you replay a Vuser script, verify that your environment is configured properly for the JDK and relevant Java classes.

## 2. Create a new Java Record Replay Protocol script

Select **File > New** and select **JAVA Record Replay** from the **Java** category.

## 3. Complete the Start Recording dialog box

Enter the details of your application in the Start Recording dialog box. For user interface details, see "[Start Recording Dialog Box](#)" on page 266.

**Note:** Java protocols can only record 32-bit applications. When you specify an application, make sure to specify a the 32-bit version. You can also specify a batch (.bat) file as the application to record.

## 4. Set the Recording Options

In the Start Recording dialog box, click Options to open the Recording Options dialog box. In the **Recorder Options** node, the **Recorded Protocol** field configures the main protocol you will be recording. If you are recording more than one Java protocol, enter the additional protocols in the **Extension List** field.

## 5. Start Recording

Record your application or batch performing the actions you want to test.

# How to Record Java Scripts Using Windows XP and 2000 Server

When recording on Windows XP and Windows 2000 servers, the Java plug-in may be incompatible with VuGen's recorder. To insure proper functionality, perform the following procedure after the installation of the java plug-in, before recording a script.

## Configure Your Machine for Recording CORBA or RMI Sessions

1. Open the Java Plug-in from the Control Panel. Select **Start > Settings > Control Panel** and open the **Java Plug-in** component. The Basic tab opens.
2. Clear the **Enable Java Plug-In** check box and click **Apply**. Then, reselect the **Enable Java Plug-In** check box and click **Apply**.
3. Open the Browser tab. Clear the **Microsoft Internet Explorer** check box and click **Apply**. Then, reselect the **Microsoft Internet Explorer** check box and click **Apply**.

## How to Run a Script as Part of a Package

This section is not relevant for Jacada type scripts.

When creating or recording a Java script, you may need to use methods from classes in which the method or class is protected. When attempting to compile such a script, you receive compilation errors indicating that the methods are not accessible.

To use the protected methods, add the Vuser to the package of required methods. At the beginning of your script, add the following line:

```
package a.b.c;
```


where **a.b.c** represents a folder hierarchy. VuGen creates the a/b/c folder hierarchy in the user folder and compiles the **Actions.java** file there, thus making it part of the package. Note that the **package** statement is not recorded—you need to insert it manually.

## How to Manually Insert Java Methods

You use the Java Function navigator to view and add Java functions to your script. You can customize the function generation settings by modifying the configuration file. For more information, see ["General > Script Node" on page 203](#).

### Insert Java Functions

1. Click within your script at the desired point of insertion.
2. Select **Insert > Insert Java Function**. The Insert Java Function dialog box opens. The lower part of the dialog box displays a description of the Java object.
3. Click **Locations**. The Locations dialog box opens. By default, VuGen lists the paths defined in the CLASSPATH environment variable.



4. Click **Browse** to add another path or archive to the list. To add a path, select **Browse > Folder**. To add an archive (**jar** or **zip**), select **Browse > File**. When you select a folder or a file, VuGen inserts it in the **Add Location** box.
5. Click **Add** to add the item to the list.
6. Repeat steps 4 and 5 for each path or archive you want to add.
7. Select or clear the check boxes to the left of each item in the list. If an item is checked, its members will be listed in the Java Class navigator.
8. Click **OK** to close the Locations dialog box and view the available packages.
9. Click the plus and minus signs to the left of each item in the navigator, to expand or collapse the trees.
10. Select an object and click **Paste**. VuGen places the object at the location of the cursor in the script. To paste all the methods of a class into your script, select the class and click **Paste**.
11. Repeat the previous step for all of the desired methods or classes.
12. Modify the parameters of the methods. If the script generation setting **DefaultValues** is set to **true**, you can use the default values inserted by VuGen. If **DefaultValues** is set to **false**, you must add parameters for all methods you insert into the script.

In addition, modify any return values. For example, if your script generated the following statement "(String)=LavaVersion.getVersionId();", replace (String) with a string type variable.

13. Add any necessary statements to your script such as imports or Vuser API Java functions (described in "[Java Vuser Protocol - Manually Programming Scripts](#)" on page 667).
14. Save the script and run it from VuGen.

## How to Manually Configure Script Generation Settings

You can customize the way the navigator adds methods to your script.

To view the configuration setting, open the **jquery.ini** file in VuGen's dat folder.

```
[Display]
FullClassName=False
[Insert]
AutoTransaction=False
DefaultValues=True
CleanClassPaste=False
```


### Class Name Path

The **FullClassName** option displays the complete package and class name in the Java Function navigator. This option does not affect the way the functions are added into the script—it only affects the way the classes are displayed in the navigator. By default, this option is set to false. If your packages have many classes and you are unable to view the package and class names at the same time, you should enable this option.

FullClassName enabled	FullClassName disabled
	

### Automatic Transactions

The **AutoTransaction** setting creates a Vuser transaction for all methods. When you enable this option, VuGen automatically encloses all Java methods with **lr.start\_transaction** and **lr.end\_transaction** functions. This allows you to individually track the performance of each method. This option is disabled by default.



The screenshot shows the LoadRunner Virtual User Generator interface for General-Java. The window title is "Virtual User Generator - [ejb1.usr - General-Java]". The menu bar includes File, Edit, View, Insert, Vuser, Actions, Tools, Window, and Help. The toolbar contains various icons for file operations like Open, Save, Print, and a set of actions. The main editor area displays the following Java code:

```

public int action() {

    lr.start_transaction("get_host_name");
    (String) = lr.get_host_name();
    lr.end_transaction("get_host_name", lr.AUTO);

    lr.start_transaction("isSystemClass");
    (boolean) = isSystemClass((String) "");
    lr.end_transaction("isSystemClass", lr.AUTO);
}

```

At the bottom of the editor, there is a status bar with the message "For Help, press F1.", and indicators for Col:1, Line:84, and INS.

## Default Parameter Values

The **DefaultValues** setting includes default values for all methods you paste into your script. This option is enabled by default and inserts a null for all objects. If you disable this option, you must manually insert parameter values for all functions in the script. The following table illustrates the DefaultValues flag enabled and disabled.

DefaultValues enabled	DefaultValues disabled
<pre> lr.message((String) ""); lr.think_time((int)0); lr.enable_redirection((boolean)false); lr.save_data((byte[])null, (String) "");</pre>	<pre> lr.message((String)); lr.think_time((int)); lr.enable_redirection((boolean)); lr.save_data((byte[]), (String));</pre>

## Class Pasting

The **CleanClassPaste** setting pastes a class so that it will compile cleanly: with an instance returning from the constructor, with default values as parameters, and without a need for import statements. Using this option, you will most likely be able to run your script without any further modifications. If you disable this option (default), you may need to manually define parameters and include import statements. Note that this setting is only effective when you paste an entire class into your script—not when you paste a single method.

The following segment shows the `toString` method pasted into the script with the **CleanClassPaste** option enabled.

```

_class.toString();
// Returns: java.lang.String
```

The same method with the **CleanClassPaste** option disabled is pasted as follows:

```
(String) = toString();
```

The next segment shows the **NumInserter** Constructor method pasted into the script with the CleanClassPaste option enabled.

```
utils.NumInserter _numinserter = new utils.NumInserter
    ((java.lang.String) "", (java.lang.String) "", (java.lang.String) ""
"...");
// Returns: void
```

The same method with the CleanClassPaste option disabled is pasted as:

```
new utils.NumInserter((String) "", (String) "", (String) "", ...);
```

## How to Create a Custom Java Filter

This task describes how to create a custom Java filter. For background information, see "[Java Custom Filters - Overview](#)" on page 656.

For details of the Hook File structure, see "[Hook File Structure](#)" on the next page.

When preparing a script, you may need to customize the filter several times in order to achieve the optimal filter. An optimal filter records the relevant methods without introducing a large number of irrelevant calls to the script.

**Note:** If you plan to add manual code to your script such as control flow or message statements, make sure to do so after you have a functional script that runs inside VuGen. The reason for this, is that if you re-record a script after modifying the filters, it will overwrite all manual changes.

### Define a Custom Java Filter

1. Create a new filter based on one of the built-in filters by modifying the **user.hooks** file which is located in the product's **classes** folder. For structural details about the user.hook file, see "[Hook File Structure](#)" on the next page.
2. Open the Recording Options (Ctrl+F7) and select the **Log Options** node. Select the Log Level to **Detailed**.
3. Record your application. Click **Start Record** (Ctrl + R) to begin and **Stop** (Ctrl + F5) to end.
4. View the script's steps. If you can determine the business logic from the steps and apply correlation, you may not need to create custom filters. If, however, the script is very long or hard to maintain and correlate, you should customize the script's filter.
5. Try to identify the high-level method in the call that captures or wraps one or more client server calls. You can do this by opening the AUT source files (if they are available) or by viewing a Stack Trace of the script.
6. Set the filter to include the relevant methods. For more information, see "[Java Custom Filters - Determining which Elements to Include](#)" on page 657.

7. Record the application again. You should always rerecord the application after modifying the filter.
8. Repeat steps 4 through 7 until you get a simple script which can be maintained and correlated.
9. Correlate the script. In order for your test to run properly, you may need to insert a correlation to capture a value and use it at a later point in the script. For more information about the built-in correlation mechanism, see "[How to Correlate Scripts - Java Scripts - Serialization](#)" on page [296](#).

**Note:** Do not modify any of the other .hooks file as it might damage the VuGen recorder.

Adding custom hooks to the default recorder is a complicated task and should be considered thoroughly as it has both functional and performance consequences.

Incorrect hooking definitions can lead to incorrect scripts, slow recording, and application freeze-up.

## Hook File Structure

The following section describes the structure of a typical .hooks file:

```
[Hook-Name]
class      = MyPackage.MyClass
method     = MyMethod
signature  = ()V
ignore_c1 =
ignore_mtd =
ignore_tree =
cb_class   = mercury.ProtocolSupport
cb_mtd    =
general_cb = true
deep_mode  = soft | hard
make_methods_public = true | false
lock       = true | false
```

The hook files are structured as .ini files where each section represents a hook definition. Regular expressions are supported in some of the entries. Any entry that uses regular expression must start with a '!'.

### Hook-Name

Specifies the name of this section in the hooks file. Hook-Name must be unique across all hooks files. A good practice is to give the fully qualified class name and method. For example:

[javax.jms.Queue.getQueueName]

### Class

A fully qualified class name. Regular expression can be used to include several classes from the same package, a whole package, several packages, or any class that matches a name. For

example:

```
Class = !javax\.jms\.*
```

## **Method**

The simple name of the method to include. Regular expressions can be used to include more than one method from the class. For example:

```
Method = getQueueName
```

## **Signature**

The standard Java internal type signature of the method. To determine the signature of a method, run the command `javap -s class-name` where `class name` is the fully qualified name of the class. Regular expressions can be used to include several methods with the same name, but with different arguments. For example:

```
Signature = !.*
```

## **ignore\_cl**

A specific class to ignore from the classes that match this hook. This can be a list of comma separated class names. Each item in the list can contain a regular expression. If an item in the list contains a regular expression, prepend a '!' to the class name. For example:

```
Ignore_cl = !com.hp.jms.Queue,!com\.\hp\..*
```

## **ignore\_mtd**

A specific method to ignore. When the loaded class method matches this hook definition, this method will not be hooked. The method name must be the simple method name followed by the signature (as explained above). To ignore multiple methods, list them in a comma separated list. To use a regular expression, prepend a '!' to the method name. For example:

```
Ignore_cl = open, close
```

## **ignore\_tree**

A specific tree to ignore. When the name of the class matches the ignore tree expression, any class that inherits from it will not be hooked, if it matches this hooks definition. To ignore multiple trees, list them in a comma separated list. To use a regular expression, prepend a '!' to the class name. This option is relevant only for hooks that are defined as deep.

## **cb\_class**

The callback class that gets the call from the hooked method. It should always be set to **mercury.ProtocolSupport**.

## **cb\_mtd**

A method in the callback class that gets the call from the hooked method. If omitted, it uses the default, **general\_rec\_func**. For cases where you just need to lock the subtree of calls, use **general\_func** instead.

## **general\_cb**

The general callback method. This value should always be set to **true**.

## Deep\_mode

Deep mode refers to classes and interfaces that inherit or implement the class or interface that the hook is listed for. The inherited classes will be hooked according to the type of hook: **Hard**, **Soft**, or **Off**.

- **Hard.** Hooks the current class and any class that inherits from it. If regular expressions exist, they are matched against every class that inherits from the class in the hook definition. Interface inheritance is treated the same as class inheritance.
- **Soft.** Hooks the current class and any class that inherits from it, only if the methods are overridden in the inheriting class. If the hook lists an interface, then if a class implements this interface those methods will be hooked. If they exist in classes that directly inherit from that class they will also be hooked. However, if the hook lists an interface and a class implements a second interface that inherits from this interface, the class will not be hooked.

**Note:** Regular expressions are not inherited but converted to actual methods.

- **Off.** Only the class listed in the hook definition and the direct inheriting class will be hooked. If the hook lists an interface, only classes that directly implement it will be hooked.

## make\_methods\_public:

Any method that matches the hook definition will be converted to public. This is useful for custom hooks or for locking a sub tree of calls from a non-public method.

Note that this applies only during record. During replay, the method will use the original access flags. In the case of non-public methods, it will throw `java.lang.VerifyError`.

## Lock

When set to **true**, it locks the sub tree and prevents the calling of any method originating from the original method.

When set to **false**, it will unlock the sub tree, record any method originating from the current method (if it is hooked), and invoke the callback.

# Java Icon Reference List

The following table describes the icons that represent the various Java objects:

Icon	Item	Example
	Package	<code>java.util</code>
	Class	<code>public class Hashtable extends java.util.Dictionary implements java.lang.Cloneable, java.io.Serializable</code>
	Interface Class (gray icon)	<code>public interface Enumeration</code>

Icon	Item	Example
	Method	public synchronized java.util.Enumeration keys ()
	Static Method (yellow icon)	public static synchronized java.util.TimeZone getTimeZone
	Constructor Method	public void Hashtable ()

## Java Vuser Protocol - Manually Programming Scripts

### Manually Programming Java Scripts - Overview

To prepare Vuser scripts using Java code, use the **Java** type Vusers. This Vuser type supports Java on a protocol level. The Vuser script is compiled by a Java compiler and supports all of the standard Java conventions. For example, you can insert a comment by preceding the text with two forward slashes "://".

The first step in creating a Java compatible Vuser script, is to create a new Vuser script template of the type **Java Vuser**. Then, you program or paste the desired Java code into the script template. You can add Java Vuser functions to enhance the script and parameterize the arguments to use different values during iterations.

The Java Vuser script runs as a scalable multi-threaded application. If you include a custom class in your script, make sure that the code is thread-safe. Code that is not thread-safe may cause inaccurate results. For code that is not thread-safe, run the Java Vusers as processes. This creates a separate Java Virtual Machine for each process, resulting in a script that is less scalable.

After you prepare a script, run it as a standalone test from VuGen. A Java compiler (javac), checks it for errors and compiles the script.

After you create a script, you integrate it into your environment: a LoadRunner scenario, Performance Center load test, or Business Process Monitor configuration.

### Java Protocol Programming Tips

When programming a Java Vuser script, you can paste ready-made code segments into scripts or import ready-made classes in order to invoke their methods. If Vusers need to run as threads under the Controller (for scalability reasons), you need to make sure that all of the imported code is thread-safe.

Thread-safety is often difficult to detect. A Java Vuser may run flawlessly under VuGen and under the Controller with a limited number of Vusers. However, problems may then occur with a large number of Vusers. Code that is not thread-safe is usually the result of static class member usage as shown in the following example:

```
import lrapi.*;
public class Actions
```

```
{
    private static int iteration_counter = 0;
    public int init() {
        return 0;
    }
    public int action() {
        iteration_counter++;
        return 0;
    }
    public int end() {
        lr.message("Number of Vuser iterations: "+iteration_counter);
        return 0;
    }
}
```

When you run one Vuser, the **iteration\_counter** member determines the number of iterations that were executed. When multiple Vusers run together as threads on a single virtual machine, the static class member **iteration\_counter** is shared by all threads, resulting in an incorrect counting. The total number of all Vusers iterations is counted.

If code is known to be non thread-safe and you still want to import it into your script, you can run the Vusers as processes. For more information on running Vusers as threads or processes, see ["Run-Time Settings" on page 317](#)

When you run a basic Java Vuser script, it usually consists of a single thread—the main thread. Only the main thread can access the Java Vuser API. If a Java Vuser spawns secondary worker threads, using the Java API may cause unpredictable results. Therefore, we recommend that you use the Java Vuser API only in the main thread. Note that this limitation also affects the **lr.enable\_redirection** function.

The following example illustrates where the LR API may and may not be used. The first log message in the execution log indicates that the value of flag is false. The virtual machine then spawns a new thread `set_thread`. This thread runs and sets flag to true, but will not issue a message to the log, even though the call to `lr.message` exists. The final log message indicates that the code inside the thread was executed and that flag was set to true.

```
boolean flag = false;
public int action() {
    lr.message("Flag value: "+flag);
    Thread set_thread = new Thread(new Runnable(){
        public void run() {
            lr.message("LR-API NOT working!");
            try {Thread.sleep(1000);} catch(Exception e) {}
            flag = true;
        }
    });
    set_thread.start();
    try {Thread.sleep(3000);} catch(Exception e) {}
    lr.message("Flag value: "+flag);
    return 0;
}
```

# Running Java Vuser Scripts

Java Vuser scripts differ from C Vuser scripts in that they are first compiled and then executed; C Vuser scripts are interpreted. VuGen locates the **javac** compiler from within the JDK installation and compiles the Java code inside the script. This stage is indicated by the **Compiling...** status message in the bottom of the VuGen window. If errors occur during compilation, they are listed in the execution log. To go to the code in your script that caused the error, double-click on the error message containing the line number of the error. Fix the error and run the script again.

If the compilation succeeds, the status message **Compiling...** changes to **Running...** and VuGen begins to execute the script. When you run the script again, VuGen runs the script without recompiling it, provided that no changes were made to the script. To debug your script further, you can use breakpoints and animated run type execution using the step option.

**Note:** If you are making calls to JNDI extensions within your script, you may encounter problems trying to run your Vusers as **threads**. This happens because JNDI requires each thread to have its own context class loader. In order to run as threads, instruct each Vuser to run with its own context class loader, by adding the following line to the beginning of the **init** section:

```
DummyClassLoader.setContextClassLoader();
```

## Editing and Running Scripts in Eclipse

Eclipse provides you with additional tools to view, edit, and debug your Java Vuser (Java Record Replay, and Java over HTTP) scripts. You can add breakpoints, view variable values, add references, and edit the script using IntelliSense. You can also run the script in a step-by-step mode for debugging.

When you save your script, VuGen creates java source files in your script's folder. You can open the solution file in Eclipse and view all of its components in the Projects Explorer.

To open the Vuser script in Eclipse, click the **Open Script in Eclipse** button  on the VuGen toolbar. If this is your first time using Eclipse from within VuGen, it will automatically install the Eclipse plugin.

Before opening a script in Eclipse, you need to set the location of the Eclipse IDE in the **Java** node of the VuGen's Scripting options. If you do not set this value, VuGen prompts you to select its location. For details, see "["Scripting Options" on page 103](#)

An additional LoadRunner toolbar menu provides access to common VuGen commands, such as Run-Time Settings, Parameter List, Run, Stop, and Create a Scenario.

LoadRunner also provides an add-in for Eclipse developers that allows you to create JUnit tests that can be called directly from the Controller, without having to open them in VuGen. The add-ins are located in the DVD/Additional Components folder. For details about the add-ins, see the *LoadRunner Installation Guide*.

For more information, see "[Creating Vuser Scripts or LoadRunner Tests in Visual Studio or Eclipse](#)" on page 969

## Opening Java Vuser Scripts in Eclipse

Eclipse provides you with additional tools to view, edit, and debug your Java Vuser (such as Java Record Replay and Java over HTTP) scripts. You can add breakpoints, view variable values, add references, and edit the script in the Eclipse editor using IntelliSense.

The VuGen and Eclipse integration allows you to configure the script as you would in VuGen, from the Eclipse IDE. A **Vuser** menu added to the Eclipse IDE, provides access to the Parameter List, run-time settings, run/stop control, and scenario creation.

### To open the Vuser script in Eclipse:

1. Make sure you have Eclipse 4.2 or higher on your machine, running with JDK 1.7 or higher.
2. Set the location of the Eclipse IDE in the **Scripting > Java** node in VuGen's Options dialog box. For details, see "["Scripting Options"](#) on page 103.
3. Create a Java script (Java Vuser, Java Record Replay, Java over HTTP, and so forth).
4. Click the **Open Script in Eclipse** button  on the VuGen toolbar. If this is your first time using Eclipse from within VuGen, it will automatically install the VuGen Eclipse plugin.
5. Double-click the appropriate section, such as **Actions.java**, to edit the code.
6. Use the **Vuser** menu to define parameters, configure run-time settings, and run the script directly from the Eclipse IDE.

## Compiling and Running a Script as Part of a Package

When creating a Java Vuser script, you may need to use methods in other classes in which the class or method is protected. If you try to compile this type of script, you will receive errors in the compilation stage indicating that the methods are inaccessible. To make sure that your script can access these methods, insert the package name containing these methods at the top of the script, just as you would do in a standard Java program—<package\_name>. In the following example, the script defines the just.do.it package which consists of a path:

```
package my.test;
import lrapi.*;
public class Actions
{
    :
}
```

In the above example, VuGen automatically creates the **my/test** folder hierarchy under the Vuser folder, and copies the **Actions.java** file to **my/test/Actions.java**, allowing it to compile with the relevant package. Note that the package statement must be the first line in the script, similar to Java (excluding comments).

# How to Manually Create a Java Script

This task describes how to manually create and edit a custom Java script.

## 1. Create a new script

- a. Open VuGen.
- b. Select **File > New** or click the **New** button. The New Virtual User dialog box opens.
- c. Select **Custom > Java Vuser** from the Select Vuser type list, and click **OK**. VuGen displays a blank Java Vuser script.
- d. Click the **Actions** section in the left frame to display the **Actions** class.

## 2. Insert your code into the script

After generating an empty template, you can insert the desired Java code. When working with this type of Vuser script, you place all your code in the Actions class. To view the Actions class, click **Actions** in the left pane. VuGen displays its contents in the right pane.

```
import lrapi.*;
public class Actions
{
    public int init() {
        return 0;
    }
    public int action() {
        return 0;
    }
    public int end() {
        return 0;
    }
}
```

The Actions class contains three methods: init, action, and end. The following table shows what to include in each method and when each method is executed.

Script method	Used to emulate...	Is executed when...
init	a login to a server	the Vuser is initialized (loaded)
action	client activity	the Vuser is in "Running" status
end	a log off procedure	the Vuser finishes or is stopped

### Init Method

Place all the login procedures and one-time configuration settings in the init method. The init method is only executed once—when the Vuser begins running the script. The following sample init method initializes an applet. Make sure to import the **org.omg.CORBA.ORB** function into this section, so that it will not be repeated for each iteration.

```
import org.omg.CORBA.*;
import org.omg.CORBA.ORB.*;
import lrapi.lr;
// Public function: init
public int init() throws Throwable {
    // Initialize Orb instance...
    MApplet mapplet = new MApplet("http://chaos/classes/", null);
    orb = org.omg.CORBA.ORB.init(mapplet, null);
...
}
```

### Action Method

Place all Vuser actions in the action method. The action method is executed according to the number of iterations you set in the runtime settings. For more information on the iteration settings, see "["Run-Time Settings" on page 317](#). The following sample action method retrieves and prints the Vuser ID.

```
public int action() {
    lr.message("vuser: " + lr.get_vuser_id() + " xxx");
    return 0;
}
```

### End Method

In the **end** method, place the code you want the Vuser to execute at the end of the script, such as logging off from a server, cleaning up the environment, and so forth.

The end method is only executed once—when the Vuser finishes running the script. In the following example, the end method closes and prints the end message to the execution log.

```
public int end() {
    lr.message("End");
    return 0;
}
```

## 3. Insert additional LoadRunner API functions

VuGen provides a specific Java API for Java Vuser scripts. These functions are all static methods of the `lrapi.lr` class.

The Java API functions are classified into several categories: Transaction, Command Line Parsing, Informational, String, Message, and Run-Time functions.

For further information about each of these functions, see the Function Reference (**Help > Function Reference**). Note that when you create a new Java Vuser script, the import `lrapi.*` is already inserted into the script.

#### 4. Insert additional Java functions

To use additional Java classes, import them at the beginning of the script as shown below.

Remember to add the classes folder or relevant jar file to the classpath. Make sure that the additional classes are thread-safe and scalable.

```
import java.io.*;
import lrapi.*;
public class Actions
{
...
}
```

#### 5. Add script enhancements

You add script enhancements such as rendezvous points, transactions, and output messages. For more information, see "[How to Enhance a Java Script](#)" below.

#### 6. Set the Java environment

Before running your Java Vuser script, make sure that the environment variables, path and classpath, are properly set on all machines running Vusers:

- To compile and replay the scripts, you must have complete JDK installation, either version 1.1 or 1.2, or 1.3. The installation of the JRE alone is not sufficient. It is preferable not to have more than one JDK or JRE installation on a machine. If possible, uninstall all unnecessary versions.
- The **PATH** environment variable must contain an entry for **JDK/bin**.
- For JDK 1.1.x, the **CLASSPATH** environment variable must include the **classes.zip** path, (**JDK/lib** subfolder) and all of the VuGen classes (**classes** subfolder).
- All classes used by the Java Vuser must be in the classpath—either set in the machine's **CLASSPATH** environment variable or in the **Classpath Entries** list in the Classpath node of the run-time settings.

## How to Enhance a Java Script

This task describes how to enhance custom Java scripts.

### Inserting Transactions

You define transactions to measure the performance of the server. Each transaction measures the time it takes for the server to respond to specified requests. These requests can be short or complex tasks. When working with LoadRunner, you can analyze the performance per transaction during and after the scenario run, using online monitor and graphs.

You can also specify a transaction status: lr.PASS or lr.FAIL. You can let the Vuser automatically determine if the transaction was successful, or you can incorporate it into a conditional loop. For example, in your code you can check for a specific return code. If the code is correct, you issue a lr.PASS status. If the code is wrong, you issue an lr.FAIL status.

## Mark a transaction

1. Insert **lr.start\_transaction** into the script, at the point where you want to begin measuring the timing of a task.
2. Insert **lr.end\_transaction** into the script, at the point where you want to stop measuring the task. Use the transaction name as it appears in the **lr.start\_transaction** function.
3. Specify the desired status for the transaction: lr.PASS or lr.FAIL.

```
public int action() {
    for(int i=0;i<10;i++)
    {
        lr.message("action()"+i);
        lr.start_transaction("trans1");
        lr.think_time(2);
        lr.end_transaction("trans1",lr.PASS);
    }
    return 0;
}
```

## Inserting Rendezvous Points

To emulate heavy user load on your client/server system, you synchronize Vusers to perform a task at exactly the same moment by creating a rendezvous point. When a Vuser arrives at the rendezvous point, it is held by the Controller until all Vusers participating in the rendezvous arrive.

You designate the meeting place by inserting a rendezvous function into your Vuser script.

## Insert a Rendezvous Point

- Insert an lr.rendezvous function into the script, at the point where you want the Vusers to perform a rendezvous.

```
public int action() {
    for(int i=0;i<10;i++)
    {
        lr.rendezvous("rendz1");
        lr.message("action()"+i);
        lr.think_time(2);
    }
    return 0;
}
```

## Obtaining Vuser Information

You can add the following functions to your Vuser scripts to retrieve Vuser information:

<b>lr.get_attrib_string</b>	Returns a string containing command line argument values or runtime information such as the Vuser ID or the load generator name.
<b>lr.get_group_name</b>	Returns the name of the Vuser's group.
<b>lr.get_host_name</b>	Returns the name of the load generator executing the Vuser script.
<b>lr.get_master_host_name</b>	Returns the name of the machine running the LoadRunner Controller or Business Process Monitor.
<b>lr.get_scenario_id</b>	Returns the ID of the current scenario. (LoadRunner only)
<b>lr.get_vuser_id</b>	Returns the ID of the current Vuser. (LoadRunner only)

In the following example, the `lr.get_host_name` function retrieves the name of the computer on which the Vuser is running.

```
String my_host = lr.get_host_name();
```

For more information about the above functions, see the Function Reference ([Help > Function Reference](#)).

## Issuing Output Messages

When you run a scenario, the Controller Output window displays information about script execution. You can include statements in a Vuser script to send error and notification messages to the Controller. The Controller displays these messages in the Output window. For example, you could insert a message that displays the current state of the client application. You can also save these messages to a file.

**Note:** Do not send messages from within a transaction. Doing so lengthens the transaction execution time and may skew the actual transaction results.

You can use the following message functions in your Vuser script:

<b>lr.debug_message</b>	Sends a debug message to the Output window.
<b>lr.log_message</b>	Sends a message to the Vuser log file.
<b>lr.message</b>	Sends a message to the Output window.
<b>lr.output_message</b>	Sends a message to the log file and Output window with location information.

In the following example, `lr.message` sends a message to the output indicating the loop number:

```
for(int i=0;i<10;i++)
{
    lr.message("action()"+i);
```

```

    lr.think_time(2);
}

```

For more information about the message functions, see the Function Reference ([Help > Function Reference](#)).

You can instruct the Vusers to redirect the Java standard output and standard error streams to VuGen's Execution log. This is especially helpful when you need to paste existing Java code or use ready-made classes containing **System.out** and **System.err** calls in your Vuser scripts. In the execution log, standard output messages are colored blue, while standard errors are shown in red.

The following example shows how to redirect specific messages to the standard output and standard error using **lr.enable\_redirection**:

```

lr.enable_redirection(true);
System.out.println("This is an informative message..."); // Redirected
System.err.println("This is an error message..."); // Redirected
lr.enable_redirection(false);
System.out.println("This is an informative message..."); // Not redirected
System.err.println("This is an error message..."); // Not redirected

```

**Note:** When you set **lr.enable\_redirection** to **true**, it overrides all previous redirections. To restore the former redirections, set this function to **false**.

For additional information about this function, see the Function Reference ([Help > Function Reference](#)).

## Emulating User Think Time

The time that a user waits between performing successive actions is known as the think time. Vusers use the **lr.think\_time** function to emulate user think time. In the following example, the Vuser waits two seconds between loops:

```

for(int i=0;i<10;i++)
{
    lr.message("action()"+i);
    lr.think_time(2);
}

```

You can use the think time settings as they appear in the script, or a factor of these values. To configure how Vusers handle think time functions, open the runtime settings dialog box. For more information, see "[Run-Time Settings](#)" on page 317.

For more information about the **lr.think\_time** function, see the Function Reference ([Help > Function Reference](#)).

## Handling Command Line Arguments

You can pass values to a Vuser script at runtime by specifying command line arguments when you run the script. You insert command line options after the script path and filename in the Controller or Business Process Monitor. There are three functions that allow you to read the command line arguments, and then to pass the values to a Vuser script:

<b>lr.get_attrib_double</b>	Retrieves double precision floating point type arguments
<b>lr.get_attrib_long</b>	Retrieves long integer type arguments
<b>lr.get_attrib_string</b>	Retrieves character strings

Your command line should have the following format, where the arguments and their values are listed in pairs after the script name:

```
script_name - argument argument_value -argument argument_value
```

The following example shows the command line string used to repeat script1 five times on the machine pc4:

```
script1 -host pc4 -loop 5
```

For more information on the command line parsing functions, see the Function Reference ([Help > Function Reference](#)). For more information on how to insert the command line options, see the *LoadRunner Controller, Performance Center, or HP Business Service Management* documentation.

## Troubleshooting and Limitations - Java Protocol

This section describes troubleshooting and limitations for the Java protocol.

- When recording on Internet Explorer 8 using the Java protocol, you must first close all instances of Internet Explorer before LoadRunner opens an Explorer instance for the record session.
- Java Record Replay Protocol: Recording of JMS applications requires JDK version 1.7 or 1.6u32 and lower.

## Java over HTTP Protocol

### Java over HTTP Protocol Overview

The Java over HTTP protocol is designed to record java-based applications and applets. It produces a Java language script using web functions. This protocol is distinguished from other Java protocols in that it can record and replay Java remote calls over HTTP.

**Note:** Java over HTTP supports asymmetric Java object traffic. This means that object serialization traffic is recognized even when it is on only one side of the communication. This occurs when the request is serialization and the response is plain HTTP, or vice versa.


## Viewing Responses and Requests in XML Format

Note that this topic applies to the Java over HTTP protocol only.

For each request and response, you can view the corresponding XML that represents the binary java object during the recording phase.

## **View XML data**

1. Locate the target request or response section in the code. Right-click the commented **RequestBodyX.xml** or **ResponseBodyX.xml**.
  2. Select **View XML**. The XML is displayed in a separate window.



# How to Record with Java over HTTP

To record with Java over HTTP, you must specify which .jar files to use in order to deserialize the recorded data.

This topic describes how to locate the relevant .jar files and add them to the classpath.

# Recording Java Applets

If your application uses Java Applets, you need to find the relevant .jar files and enable them in the classpath.

1. Clear the JAR cache by selecting **Control Panel > Java > General Tab > Temporary Internet Files > Settings > Delete Files**.
  2. Open your application and perform a few business processes to repopulate the JAR cache with .jar files from your application. When you are finished, close your application.
  3. Select **Control Panel > Java > General Tab > Temporary Internet Files > View**. This lists the JAR cache and should contain only the .jar files used by your application.
  4. Download the files. Try the options below in the order in which they appear. When you succeed, proceed to the next step to add the .jar files to the classpath.

- a. Option 1: For each .jar file, go to the listed URL and download the file. If you cannot download one or more of the .jar files, continue with the next option.
  - b. Option 2: Clear the cache again by selecting **Control Panel > Java > General Tab > Temporary Internet Files > Settings > Delete Files**. Open your application again and perform a few business processes. Do not close your application. Open the Java Console. There should be a message for each .jar file telling you the location it is stored in a temporary file on your computer. The files are usually hashed and don't have .jar extensions. Change the name (including changing each extension to .jar) and copy the file to a known location.
  - c. Option 3: If the files don't show up in the Java console, locate the temporary folder as listed in **Control Panel > Java > General Tab > Temporary Internet Files > Settings > Location**. Open the specified location and rename all the files in the sub-folders to .jar. Do not rename all the files in the main folder.
5. Add the .jar files to the classpath in the **Recording Options > Java Environment Settings > Classpath** node. For more information, see [Java > Classpath Node](#).

## Recording Local Java Applications

If you are recording a local Java application (not an applet), all of the .jar files already exist on your computer.

1. Look in the batch file that launched the application. All of the .jar files that are referenced should be added to the classpath.
2. If you cannot locate or understand the batch file, add all of the .jar files from the application folder and sub-folders to the classpath.
3. Add the .jar files to the classpath in the **Recording Options > Java Environment Settings > Classpath** node. For more information, see [Java > Classpath Node](#).

## How to Debug Java over HTTP scripts

This task describes how to debug Java over HTTP Vuser scripts by comparing the request and response data from the record and replay stages.

### 1. Add arguments to the VM Param Node

Select **Replay > Run-Time Settings > Java VM** node. In the **Additional VM Parameters** field, enter the following string:

```
-DdumpServerRequests=true -DdumpServerResponses=true
```

### 2. Compare record and replay data

In the Solution Explorer, right-click the script name and select **Open Script Folder**. The data from the recording phase is in the main folder. The data from the replay phase is in the replay folder.

The files that follow the format RequestBodyX contain the request data. The files that follow the format ResponseBodyX contain the response data.

To compare the record and replay data for the purposes of debugging, compare the files with identical names from the recording and replay phases. For example, compare the RequestBody1 file from the main folder (recording phase) to the RequestBody1 file from the replay folder. Normally, the files should be identical. Cases where the files are not identical may indicate problems in the script.

### 3. Remove arguments before load testing

Return to the Java VM node and the items you added to the Additional VM Parameters field.

## How to Insert Parameters into Java over HTTP Scripts

Parameter functions can be added for each response or request body text in a specific location. This location is indicated by a blank line, usually one to two lines below the start of the response or request body. In the example below, parameter functions can be added to the blank lines in each requestBody section.

```
/////////// requestBody2.xml //////////
RemoteInvocation RemoteInvocation_getUsernameList2 =
    (RemoteInvocation) JavaHTTP.readObject(RemoteInvocationBA0);
//INSERT PARAMETERIZATION AND CORRELATION CODE HERE
RemoteInvocationResult RemoteInvocationResult_ArrayList2 =
    (RemoteInvocationResult) JavaHTTP.sendSerialized(RemoteInvocation_getUsernameList2, 2,
"ObjectsDeserializerDefaultImpl",
"OrderService-httplibInvoker",
"URL=http://kalimanjaro.devlab.ad:8080/jpetstore/remoting/OrderService-httplibInvoker",
new String[] {
    "Method=POST",
    "Resource=0",
    "RecContentType=application/x-java-serialized-object",
    "Referer=",
    "Mode=HTML",
    "EncType=application/x-java-serialized-object",
    LAST}); // 2 is the number of the header file, record time response is at file responseBody2.xml

/////////// requestBody3.xml //////////
RemoteInvocation RemoteInvocation_getCategoryList3 =
    (RemoteInvocation) JavaHTTP.readObject(RemoteInvocationBA1);
//INSERT PARAMETERIZATION AND CORRELATION CODE HERE
RemoteInvocationResult RemoteInvocationResult_ArrayList3 =
    (RemoteInvocationResult) JavaHTTP.sendSerialized(RemoteInvocation_getCategoryList3, 3,
"ObjectsDeserializerDefaultImpl",
"OrderService-httplibInvoker_2",
"URL=http://kalimanjaro.devlab.ad:8080/jpetstore/remoting/OrderService-httplibInvoker",
new String[] {
    "Method=POST",
    "Resource=0",
    "RecContentType=application/x-java-serialized-object",
    "Referer=",
    "Mode=HTML",
    "EncType=application/x-java-serialized-object",
    LAST}); // 3 is the number of the header file, record time response is at file responseBody3.xml
```

## Java over HTTP - Troubleshooting and Limitations

This section describes troubleshooting and limitations for the Java over HTTP protocol.

## Limitations

- JDK 1.5 or higher is required.
- Lazy evaluating objects are not supported, for example hibernate in lazy mode.
- If there are stateful serialization mechanisms on the application server, this can interfere with LoadRunner deserialization and result in unserialized data and unexpected errors.
- The following menu items are not available for this protocol:
  - Insert > New Step / Start Transaction / End Transaction / Rendezvous

## Disable Exception Error Checking

If you are receiving exception errors and you are sure that the error is irrelevant, VuGen allows you to disable all such error messages. To do this, select **Replay > Run-Time Settings > Java VM** node. In the **Additional VM Parameters** field, and append the following string to the end of the current entry:

```
-DvalidateServerResponse=false
```

Additionally, you can change the error checking behavior of a specific step by adding a closing argument to the sendSerialized function in script view. For more information, see the Function Reference.

## Cannot Correlate Private Object Members

When you need to correlate or parameterize data that is a private member of an object, you can use the **Irapi.Ir2.fieldSetter** and **Irapi.Ir2.fieldGetter** functions.

```
RemoteInvocation RemoteInvocation2 = (RemoteInvocation) JavaHTTP.readObject(RemoteInvocationBA0);
    RemoteInvocation.methodName="applyToSchool";
    Student student=RemoteInvocation.arguments[0];

    Map grades=lr2.fieldGetter(student,"grades");//grades is a private member of Student
    grades.put("Math","95");
    lr2.fieldSetter(student,"super.name","Tom");
    //Student class inherits the name field from Person. name field is a string
    lr2.fieldSetter(student,"super.ID","98764321");
    //Student class inherits the ID field from Person. ID field is an int
    RemoteInvocationResult RemoteInvocationResult_ArrayList2 =
(RemoteInvocationResult) JavaHTTP.sendSerialized(RemoteInvocation2, 2,
"ObjectsDeserializerDefaultImpl",....
```

## LDAP Protocol

## LDAP Protocol Overview

LDAP, the Lightweight Directory Access Protocol, is a protocol used to access a folder listing. The LDAP folder is composed of many LDAP entries. Each LDAP entry is a collection of attributes with a name, called a distinguished name (DN). For more information about DN, see "[Defining Distinguished Name Entries](#)" on the next page.

LDAP folder entries are arranged in a hierarchical structure that reflects political, geographic, and/or organizational boundaries. Entries representing countries appear at the top of the tree. Below them are entries representing states or national organizations. Below them might be entries representing people, organizational units, printers, documents, or just about anything else.

VuGen records communication over LDAP servers. It creates a Vuser script, with functions that emulate your actions. This includes logging in and out of the server, adding and deleting entries, and querying an entry.

## LDAP Protocol Example Script

All LDAP functions come in pairs—one for global sessions and one where you can indicate a specific session. To apply the action to all sessions, use the version without the **ex** suffix. To apply the action to a specific session, use the version with the session identifier with the **ex** suffix. For example, **mldap\_logon** logs on to the LDAP server globally, while **mldap\_logon\_ex** logs on to the LDAP server for a specific session.

In the following example, the user logs on to an LDAP server, **ldap1**. It adds an entry and then renames the OU attribute from Sales to Marketing.

```
Action()
{
    // Logon to the LDAP server
    mldap_logon("Login",
        "URL=ldap://johnsmith:tiger@ldap1:80",
        LAST);

    // Add an entry for Sally R. Jones
    mldap_add("LDAP Add",
        "DN=cn=Sally R. Jones,OU=Sales, DC=com",
        "Name=givenName", "Value=Sally", ENDITEM,
        "Name=initials", "Value=R", ENDITEM,
        "Name=sn", "Value=Jones", ENDITEM,
        "Name=objectClass", "Value=contact", ENDITEM,
        LAST);

    // Rename Sally's OU to Marketing
    mldap_rename("LDAP Rename",
        "OU=Sally R. Jones,DC=com", "OU=Marketing,DC=com");
}
```

```

    "DN=CN=Sally R. Jones,OU=Sales,DC=com",
    "NewDN=OU=Marketing",
    LAST);

// Logout from the LDAP server
mldap_logoff();
return 0;
}

```

## Defining Distinguished Name Entries

The LDAP API references objects by its **distinguished name** (DN). A DN is a sequence of **relative distinguished names** (RDN) separated by commas.

An RDN is an attribute with an associated value in the form attribute=value. The attribute names are not case-sensitive. The following table lists the most common RDN attribute types.

String	Attribute Type
<b>DC</b>	domainComponent
<b>CN</b>	commonName
<b>OU</b>	organizationalUnitName
<b>O</b>	organizationName
<b>STREET</b>	streetAddress
<b>L</b>	localityName
<b>ST</b>	stateOrProvinceName
<b>C</b>	countryName
<b>UID</b>	userid

The following are examples of distinguished names:

DN=CN=John Smith,OU=Accounting,DC=Fabrikam,DC=COM  
 DN=CN=Tracy White,CN=admin,DC=corp,DC=Fabrikam,DC=COM

The following table lists reserved characters that cannot be used in an attribute value.

Character	Description
	space or # character at the beginning of a string
	space character at the end of a string
,	comma

+	plus sign
"	double quote
\	backslash
<	left angle bracket
>	right angle bracket
;	semicolon

To use a reserved character as part of an attribute value, you must precede it with an escape character, a backslash (\). If an attribute value contains other reserved characters, such as the equal sign (=) or non-UTF-8 characters, you must encode it in hexadecimal format—a backslash followed by two hex digits.

The following are examples of DNs that include escaped characters. The first example is an organizational unit name with an embedded comma; the second example is a value containing a carriage return.

```
DN=CN=Bitwise,OU=Docs\,, Support,DC=Fabrikam,DC=COM
DN=CN=Before\0DAfter,OU=Test,DC=North America,DC=Fabrikam,DC=COM
```

## LDAP Connection Options

Using the **mldap\_logon\_ex** function, you control the way you login to the LDAP server.

When specifying the URL of the LDAP server, you specify how to connect and with what credentials.

When specifying the server's URL, use the following format:

```
ldap[s][username:[password]@][server[:port]]
```

The following table shows several examples of connections to LDAP servers.

Syntax	Description
ldap://a:b@server.com:389	Connects to the server (to 389 port) and then binds with username "a" , password "b"
ldap://:@server.com	Connects to server (to default unsecured port 389) then binds anonymously with a NULL username and password
ldaps://a:@server.com	Connects to server (to default secured port 636) and then binds with username "a", password ""
ldap://@server.com, ldap://server.com	Connects to server without binding
ldap://a:b@	Binds with username "a", password "b, executing a bind on the existing session without reconnecting

Syntax	Description
ldap://:@	Binds anonymously with a NULL username and password (executes bind on existing session without reconnecting)

You can also specify LDAP modes or SSL certificates using the following optional arguments:

- **Mode.** The LDAP call mode: *Sync* or *Async*
- **Timeout.** The maximum time in seconds to search for the LDAP server
- **Version.** The version of the LDAP protocol version 1,2, or 3
- **SSLCertDir.** The path to the SSL certificates database file (cert8.db)
- **SSLKeysDir.** The path to the SSL keys database file (key3.db)
- **SSLKeyNickname.** The SSL key nickname in the keys database file
- **SSLKeyCertNickname.** The SSL key's certificate nickname in the certificates database file
- **SSLSecModule.** The path to the SSL security module file (secmod.db)
- **StartTLS.** Requires that the StartTLS extension's specific command must be issued in order to switch the connection to TLS (SSL) mode

For detailed information about these arguments, see the Function Reference ([Help > Function Reference](#)).

## Troubleshooting and Limitations - LDAP

This section describes troubleshooting and limitations for the LDAP protocol.

- If an LDAP version 3 script fails during replay, modify the **mldpa\_logon\_ex** statement to specify the version number by adding "Version=3" after "URL=..."
- When recording LDAP scripts, the binary parameter values for certain LDAP functions (such as **mldap\_add** or **mldap\_modify**) are not recorded. Recording of binary parameters is part of the protocol's extended functionality and is not supported by VuGen.

## Mailing Service Protocols

### Mailing Service Protocols Overview

The Mailing Service protocols emulate users working with email clients, viewing and sending emails. The following mailing services are supported:

- Internet Messaging (IMAP)

- MS Exchange (MAPI)
- Post Office Protocol (POP3)
- Simple Mail Transfer Protocol (SMTP)

The mail protocols support both record and replay, with the exception of MAPI that supports only replay.

## IMAP Protocol Overview

IMAP Vuser script functions record the Internet Mail Application Protocol.

Each IMAP function begins with an **imap** prefix. For detailed syntax information on these functions, see the Function Reference (**Help > Function Reference**).

In the following example, the **imap\_create** function creates several new mailboxes: Products, Solutions, and FAQs.

```
Actions()
{
    imap_logon("ImapLogon",
        "URL=imap://johnd:letmein@exchange.mycompany.com",
        LAST);
    imap_create("CreateMailboxes",
        "Mailbox=Products",
        "Mailbox=Solutions",
        "Mailbox=FAQs",
        LAST);
    imap_logout();
    return 1;
}
```

**Note:** VuGen currently supports only the IMAP LOGIN authentication method, but not the AUTHENTICATE method.

## MAPI Protocol Overview

MAPI Vuser script functions generate activity to and from an MS Exchange server. Each MAPI function begins with a **mapi** prefix. For detailed syntax information on these functions, see the Function Reference (**Help > Function Reference**). Note that recording of Vuser scripts is not supported for the MAPI protocol.

**Note:** To run MAPI scripts, you must define a mail profile on the machine running the script. For example, install Outlook Express, set it as the default mail client, and create a mail account. Alternatively, install Microsoft Outlook, set it as the default mail client, create a mail account and create a mail profile. To create a mail profile in Microsoft Outlook, select **Settings > Control Panel > Mail > Show Profiles** and add a mail profile.

In the following example, the **mapi\_send\_mail** function sends a sticky note through an MS Exchange server.

```
Actions()
{
    mapi_logon("Logon",
        "ProfileName=John Smith",
        "ProfilePass=Tiger",
        LAST);
    //Send a Sticky Note message
    mapi_send_mail("SendMail",
        "To=user1@techno.merc-int.com",
        "Cc=user0002t@techno.merc-int.com",
        "Subject=<GROUP>:<VUID> @ <DATE>",
        "Type=Ipm.StickyNote",
        "Body=Please update your profile today.",
        LAST);
    mapi_logout();
    return 1;
}
```

## POP3 Protocol Overview

POP3 Vuser script functions emulate actions using the Post Office Protocol, POP3. Each function begins with a **pop3** prefix. For detailed syntax information on these functions, see the Function Reference ([Help > Function Reference](#)).

In the following example, the **pop3\_retrieve** function retrieves five messages from the POP3 server.

```
Actions()
{
    pop3_logon("Login", "
        URL=pop3://user0004t:my_pwd@techno.merc-int.com",
        LAST);
    // List all messages on the server and receive that value
    totalMessages = pop3_list("POP3", LAST);
    // Display the received value (It is also displayed by the pop3_list function)
    lr_log_message("There are %d messages.\r\n\r\n", totalMessages);
    // Retrieve 5 messages on the server without deleting them
    pop3_retrieve("POP3", "RetrieveList=1:5", "DeleteMail=false", LAST);
    pop3_logoff();
    return 1;
}
```

## SMTP Protocol Overview

SMTP Vuser script functions emulate the Single Mail Transfer Protocol traffic. Each SMTP function begins with an **smtp** prefix. For detailed syntax information on these functions, see the Function Reference ([Help > Function Reference](#)).

In the following example, the **smtp\_send\_mail** function sends a mail message, through the SMTP mail server, techno.

```
Actions()
{
    smtp_logon("Logon",
                "URL=smtp://user0001t@techno.merc-int.com",
                "CommonName=Smtp Test User 0001",
                NULL);
    smtp_send_mail(    "SendMail",
                        "To=user0002t@merc-int.com",
                        "Subject=MIC Smtp: Sample Test",
                        "MAILOPTIONS",
                        "X-Priority: 3",
                        "X-MSMail-Priority: Medium",
                        "X-Mailer: Microsoft Outlook Express 5.50.400\r\n",
                        "X-MimeOLE: By Microsoft MimeOLE V5.50.00\r\n",
                        "MAILDATA",
                        "MessageText="
                            "Content-Type: text/plain;\r\n"
                            "\tcharset=\"iso-8859-1\"\r\n"
                            "Test,\r\n"
                            "MessageBlob=16384",
                        NULL);
    smtp_logout();
    return 1;
}
```

## Mobile Protocols

### Mobile Protocols Overview

The VuGen Mobile protocols expand LoadRunner's capability of recording user activity from mobile applications, both **native**<sup>1</sup> and **browser-based**<sup>2</sup>. With this solution you can:

- Simulate users working on mobile devices
- Create scripts based on the recording of mobile devices or emulators

### Protocol Options for Mobile

You can record user activity on a mobile device and generate scripts in VuGen using one of two protocols:

<sup>1</sup>A mobile application, such as a new service, where the application resides on the device, but communicates with the server at various intervals.

<sup>2</sup>A browser-based application that has been configured for the display of the mobile device.

-  **Mobile Application - HTTP/HTML:** A protocol enabling you to develop scripts using mobile devices or device emulators communicating with servers over HTTP. You can record network traffic into a capture file (PCAP file) and create a VuGen script. Additionally, you can use a mobile emulator on your VuGen machine to develop your scripts.
-  **TruClient Ajax - Mobile:** A protocol enabling you to record user activity in browser-based mobile applications using Ajax TruClient technology. The Ajax TruClient browser is modified to emulate the display of your mobile browser.

The following table can help you determine which protocol is most suitable for your needs:

Application Type	TruClient Ajax - Mobile	Mobile Application - HTTP/HTML
<b>Browser-based applications</b>	✓	✓
<b>Native applications</b>		✓

For details, see "[How to Select a Recording Method for Mobile Applications](#)" below

## ***How to Select a Recording Method for Mobile Applications***

You can record user activity on a mobile device and generate scripts in VuGen using one of the following protocols:

-  **Mobile Application - HTTP/HTML:** A protocol enabling you to develop scripts using mobile devices or device emulators communicating with servers over HTTP. You can record network traffic into a capture file (PCAP file) and create a VuGen script. Additionally, you can use a mobile emulator on your VuGen machine to develop your scripts.
-  **TruClient Ajax - Mobile:** A protocol enabling you to record user activity in browser-based mobile applications using Ajax TruClient technology. The Ajax TruClient browser is modified to emulate the display of your mobile browser.
-  **SMP (SAP Mobile Platform):** A protocol enabling you to create .Net based scripts using files generated by SMP. For details, see "[".NET Protocol](#)" on page 718.

The following tables summarize the requirements for the various options for recording mobile applications.

 To learn more about a specific recording method, click on the link.

#### TruClient Ajax - Mobile Protocol

If your client application....	you can use ...
<ul style="list-style-type: none"> <li>Is a browser based mobile version of a web site.</li> <li>Supports Firefox</li> </ul>	 <a href="#">Mobile TruClient</a>

#### SMP (SAP Mobile Platform)

If your client application....	you can use ...
<ul style="list-style-type: none"> <li>Is built on SMP (SAP Mobile Platform)</li> </ul>	 <a href="#">SMP (SAP Mobile Platform)</a>

#### Mobile Application - HTTP/HTMLProtocol

If your client application...	and...	you can use the...
<ul style="list-style-type: none"> <li>Communication protocol is HTML/HTTP.</li> <li>Is either browser based or native application.</li> </ul>	<ul style="list-style-type: none"> <li>Your device is in the same network as the VuGen machine.</li> <li>Your device allows proxy configuration.</li> </ul>	 <a href="#">LoadRunner Proxy</a>
<ul style="list-style-type: none"> <li>Communication protocol is HTML/HTTP.</li> <li>Is either a browser based or native application.</li> </ul>	<ul style="list-style-type: none"> <li>You do not want (or cannot) record from the actual device.</li> <li>The device, the server application and the VuGen machine are all in the same network .</li> <li>You can install the Mobile Sniffer Agent on the server machine.</li> </ul>	 <a href="#">Mobile HTTP/HTML &gt; Record &amp; Analyze Traffic</a>
<ul style="list-style-type: none"> <li>Communication protocol is HTML/HTTP.</li> <li>Is either a browser based or native application.</li> </ul>	<ul style="list-style-type: none"> <li>You have an existing capture file.</li> </ul>	 <a href="#">Mobile HTTP/HTML &gt; Analyze Traffic</a>

**Mobile Application - HTTP/HTMLProtocol, continued**

<b>If your client application...</b>	<b>and...</b>	<b>you can use the...</b>
<ul style="list-style-type: none"> <li>• Communication protocol is HTML/HTTP.</li> <li>• Is either a browser based or native application.</li> </ul>	<ul style="list-style-type: none"> <li>• You do not want (or cannot) record from the actual device.</li> <li>• Your mobile OS is Android.</li> <li>• You have a device emulator.</li> </ul>	 Mobile HTTP/HTML > Record Emulator
<ul style="list-style-type: none"> <li>• Communication protocol is HTML/HTTP.</li> <li>• Is either a browser based or native application.</li> </ul>	<ul style="list-style-type: none"> <li>• You have a <b>rooted</b><sup>1</sup> Android device.</li> <li>• You can install the <b>LoadRunner Mobile Recorder</b> application.</li> </ul>	 Mobile Recording

## Network Speed Simulation

Network Simulation for mobile protocols models the behavior of the cellular network. This enables you to test an applications taking into consideration end-to-end response time from device to server. Three configuration options are available:

### Maximum Bandwidth

This option is provided in cases where you do not wish to emulate a cellular network. This is the default setting.

### Standard Bandwidth

Network Speed Simulation for mobile protocols provides predefined settings suitable for known cellular networks:

- General Packet Radio Service (GPRS)
- Enhanced Data rates for GSM Evolution (EDGE)
- Universal Mobile Telecommunications System (UMTS)
- High-Speed Downlink Packet Access (HSDPA)
- High-Speed Downlink Packet Access Phase 2 (HSDPA phase 2)
- High-Speed Uplink Packet Access (HSUPA)

<sup>1</sup>The process of allowing privileged control to the device's subsystem.

Each network type has both a maximum and expected rate. The maximum rate represents the technology's best case performance rate while the expected rate more accurately reflects real time performance.

## Custom Bandwidth

Network Speed Simulation enables you to set custom download and upload speeds, defined in bits. You can set either a single value or range for either upload or download speed. A case where this option would be useful is when you have expected network speed from your cellular provider for a specific area.

For details on setting a custom bandwidth, see "[Network > Speed Simulation Node](#)" below.

## **Network > Speed Simulation Node**

This dialog box enables you to configure bandwidth for the mobile protocol.

<b>To access</b>	<b>VuGen &gt; Run-time settings &gt; Network &gt; Speed Simulation</b>
<b>Important information</b>	This option is only available for mobile protocols.  <a href="#">"Network Speed Simulation"</a> on the previous page

User interface elements are described below:

UI Element	Description
<b>Use maximum bandwidth</b>	Vusers run at the maximum bandwidth that is available over the network.  <b>Default value:</b> enabled.
<b>Use standard bandwidth</b>	Select a bandwidth associated with a cellular technology.
<b>Use custom bandwidth</b>	<p><b>Download speed:</b> Indicate a custom download speed in bits. Can be defined as a range or single value.</p> <p><b>Upload speed:</b> Indicate a custom upload speed in bits. Can be defined as a range or single value.</p> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>• If you select custom bandwidth and both upload speed and download speed are left blank, the default setting of maximum bandwidth will be used.</li> <li>• If you select custom bandwidth and either upload speed or download speed are left blank, the empty value is automatically set to the defined value.</li> </ul>

# Mobile Application - HTTP/HTML

## ***Recording Methods***

The Mobile Application - HTTP/HTML protocol provides the following methods for script generation:

### **Create a Script With a Capture File**

You can analyze a capture file that was created with either an external capture file utility, such as Wireshark, or VuGen's Mobile Sniffer Agent. The **Recording Wizard > Analyze Traffic** option enables you to point to the capture file, specify the source or destination IP address to include, and generate the script.

For details see:

- "[Recording Traffic into a Capture \(Sniffer\) File](#)" on the next page
- "[How to Create a Script by Analyzing Traffic](#)" on page 860
- "[Recording Wizard](#)" on page 709

### **Create a Script Using an Emulator**

For many mobile devices, there are third party emulators that you can install on your computer. Once installed, you can use the **Emulate Record** method to record and generate a script.

For details see:

- "[Recording with Emulation](#)" on page 699
- "[Recording Wizard](#)" on page 709

### **Create a Script using the LoadRunner Mobile Recorder Application**

You can record a capture file on your mobile device using the LoadRunner Mobile Recorder application.

For details see:

- "[How to Record with the Mobile Recorder](#)" on page 708
- "[LoadRunner Mobile Recording Application User Interface](#)" on page 713

### **Create a script using the LoadRunner Proxy**

The VuGen machine acts as a proxy server capturing all the traffic from the mobile device to the target server. After the business process has been recorded VuGen creates a script.

For details, see

- "Recording via a Proxy- Overview" on page 260
- "How to Record a Script via a Proxy" on page 261

## ***Recording Traffic into a Capture (Sniffer) File***


Recording application traffic to a capture file is effective when you are unable to record an application using VuGen as is the case with mobile applications. A capture file is a trace file containing a log of all TCP traffic over the network. Using a sniffer application, you obtain a dump of all of the network traffic. The sniffer captures all of the events on the network and saves them to a capture file. To generate a smaller, more manageable script, try to capture the network traffic only for the time that you perform actions in your application.

Depending on your OS and device, you have many options on where and how to record a capture file. The table below lists the some of the locations and their related advantages and disadvantages:

Capture File Source	Supported by Mobile Sniffer Agent	Advantages	Disadvantages
Mobile device using LR Mobile Recording application		Record the real traffic that comes from the device	Requires administrator permissions
VuGen with configured <b>hot spot</b> <sup>1</sup>	✓	<ul style="list-style-type: none"> <li>• Easy and intuitive</li> <li>• Administrator permission not an issue</li> </ul>	<ul style="list-style-type: none"> <li>• Not all devices support “ad hoc”</li> <li>• Captures WiFi only (Not capturing cellular network traffic)</li> </ul>
Server	✓	Record real traffic (both WiFi and cellular network traffic)	<ul style="list-style-type: none"> <li>• Requires administrator permissions</li> <li>• Requires installation of a software on the server</li> </ul>

You have the flexibility to record traffic with LoadRunner's mobile sniffer agent or record traffic with an external sniffer agent. The following flow chart illustrates the workflow for both methods:

<sup>1</sup>A WiFi connection



## Record Traffic with VuGen's Mobile Sniffer Agent

### Recording traffic on remote servers

To record traffic on a remote server you first must manually install the mobile sniffer agent on your server by copying the relevant folder from <LR installation directory>\mobileRemoteAgent to a location of your choice on your server. The following table lists the supported operating systems and their corresponding file directories:

OS	Folder
Windows OS	Win32
Linux	LinuxRH3
Mac	Mac

Once you have copied the folder, you initiate the process by typing a command line argument. For example, if you are recording in a Windows environment the command line string may look something like this:

```
mongoose-2.11.exe -e errorLog.txt -r "C:\Program  
Files\HP\LoadRunner\mobileRemoteAgent\win32" -C ".cgi" -p 80
```

Common command arguments and their descriptions:

-c	Identify the remote sniffer agent extensions. Always "cgi".
-p	Identify the port and optionally the ip address that you want the mobile sniffer agent to listen on.
-r	Location of the mobile sniffer agent. <b>Path must be absolute or the process will fail.</b>
-l	Restricts access to the mobile sniffer agent to a specific client identified by the client's IP.
-e	Name of the error log.

Note: Do not use -g option. ("digest user/password" ) There is a defect with this option.

Once a sniffer agent is installed, you manually start the agent and continue the **Record and Analyze** method from the **Recording Wizard**.

For details, see "[Recording Wizard](#)" on page 709

### CGI Configuration File Options

The CGI configuration file is located in <LR installation directory>\mobileRemoteAgent\<win32/Mac/LinuxRH3>/cgi-bin/mobileCGI.conf

You can configure the following options:

- **timeout-seconds**

Default =1800

The timeout session check stops when the process is sleeping due to traffic inactivity; the timeout session resumes as soon as the adapter is recording events.

- **max-pcap-file-size-kb**

Default = 102400

Maximum file size check stops when the process is sleeping due to traffic inactivity; the timeout session resumes as soon as the adapter is recording events.

Since traffic is first written to a buffer file and flashed to the hard drive, the maximum size may be exceeded.

- **log-file-enable**

Default = 0

#### Example of CGI configuration file

```
timeout-seconds 1800
```

```
max-pcap-file-size-kb 102400
```

```
log-file-enable 0
```

## Recording traffic on local hosts

In certain circumstances, capturing traffic directly on the application sever may not be practical. In this instance, you can capture traffic to your local computer by connect your mobile device to local host. Clicking Connect will launch the mobile sniffer agent. Continue the **Record and Analyze** method through the **Recording Wizard**.

### Configuring a hotspot on your local host

In order to record using a local host, you must first configure your machine as a hotspot. There are two ways to accomplish this, either by ad hoc or SoftAp.

Information about ad hoc and SoftAP is available from many publicly available web sites.

#### Notes:

- Not all the devices support adhoc. For example, some versions of Android do not support it.
- Since our agent is using libpcap (the same package used by Wireshark) not all network configurations will be supported by the mobile sniffer agent.
- In order for a hotspot to work, you first need to configure your firewall to support it.
- The hotspot may be implemented with NAT thus the address of the mobile will be identical to the hotspot machine.

Once hotspot as been configured on your local host, you continue to **Record and Analyze** method using the **Recording Wizard**.

For details, see "[Recording Wizard](#)" on page 709

## Capture Traffic With an External Sniffer Tool

Most UNIX operating systems have a built-in version of a capture tool. In addition, there are many downloadable capture tools such as Wireshark/tcpdump. When using external tools, make sure that all packet data is being captured and none of it is being truncated. Certain capture utilities require additional arguments. For example, tcpdump requires the -s 0 argument in order to capture the packets without truncating their data. You can also manually create a capture file using the command line utility.

The VuGen command line utility, **Irtcpdump**, is located in the **LoadRunnerInstallationDVD\Additional Components\Irtcpdump** folder. There is a separate utility for each of the platforms:

- lrtcpdump.exe (Windows)
- lrtcpdump.hp9
- lrtcpdump.ibm
- lrtcpdump.Linux
- lrtcpdump.solv4

For details, see "[How to Create a Script by Analyzing Traffic](#)" on page 860

In addition, there are many down-loadable capture tools such as Wireshark/tcpdump. Once the capture file has been created, you can generate the script by using the **Analyze Traffic** method from the **Recording Wizard**.

For details, see "[Recording Wizard](#)" on page 709

## Troubleshooting Missing Packets

**Issue:** Your script is missing steps you recorded into a capture file.

You encounter the following warning in the **Output Pane > Code generation** tab:

Warning: One or more responses are missing or have missing packets. Therefore, a step may appear to be missing in the script.

This issue can be caused if the recording was stopped before all the responses were received.

If the script is generated from a .pcap file, check if the file has missing packets.

This error may be caused by unnecessary network activity on the recorded machine, which can cause the capturing application to drop packets.

**Steps to Resolve:** Ensure that the capturing machine has no unnecessary network traffic in the background.

**Note:** To workaround this issue, select **Recording Options > HTTP Properties >Advanced > Create steps with missing responses** to generate steps for HTTP requests that are missing server responses.

## Analyzing Traffic


You will need to specify which IP address the Recording Wizard should analyze. The **AnalyzeTraffic** option from the **Recording Wizard** provides two methods to specify which IP address's traffic to include in the script VuGen is generating. As illustrated in the graphic, traffic is identified either from the server side or from the client side. You will need to specify which IP address's traffic, either client or server side, to include in the script.

### Server Side (Destination)

You can configure multiple IP addresses on one server. For example you may be running SMTP, FTP and a web server all on the same computer with unique IP addresses. When the sniffer agent creates the capture file it will include all events to all the services on the server. However, by configuring server side traffic, you can specify the IP address and port where your application under test resides. This method is useful when you are certain that only one client is communicating with the server.

### **Client Side (Source)**

You can identify the client that has been communicating with the server as the IP address to analyze. This way, only the events from the client's IP address will be included in the script VuGen will generate.



### **Filter Options**

You can specify additional IP addresses to either include or exclude during code generation **Recording Options > Traffic Analysis > Traffic Filters**. For details, see "["Traffic Analysis > Traffic Filter" on page 243](#).

## **Recording with Emulation**

Testing mobile applications with an emulator is a solid solution for many mobile devices. You can install a third party emulation application on your local computer and record events with the Record Emulator method from the Recording Wizard.

The Record Emulator method requires three settings in order to start the emulator:

- Emulator to record
- Command line
- Working directory

For details, see "["Record Emulation Dialog Box" on page 712](#).

Below is a table including emulator download site and **Record Emulator** settings for Web OS:

Mobile OS	Link to Download SDK	Emulator to record (example)	Command line (example)	Working directory (example)
Android	<a href="#">Android Emulator Download</a>	C:\Program Files\Android\android-sdk-windows\tools\emulator.exe	@Android_v2.2	C:\Program Files\Android\android-sdk-windows\tools
Blackberry	<a href="#">Blackberry Emulator Download</a>	C:\Program Files\Research In Motion\BlackBerry Smartphone Simulators 6.0.0\6.0.0.337 (9800)\fledge.exe	/app=Jvm.dll /handheld=9800 /session=9800 /app-param=DisableRegistration /app-param=JvmAIXConfigFile:9800.xml /data-port=0x4d44 /data-port=0x4d4e /pin=0x2100000A  (See " <a href="#">Recording with Emulation</a> " on the previous page)	C:\Program Files\Research In Motion\BlackBerry Smartphone Simulators 6.0.0\6.0.0.337 (9800)
Windows 8	<a href="#">Windows Mobile Emulator Download</a>	C:\Program Files\Microsoft SDKs\Windows Phone\v7.0\Tools\xdeLauncher\xdeLauncher.exe	"Windows Phone 7" "Windows Phone 7 Emulator"	C:\Program Files\Microsoft SDKs\Windows Phone\v7.0\Tools\xdeLauncher


## Recording with a Mac iPhone Emulator

Using the Record and Analyze method from the Recording Wizard, you can record an iPhone script using an emulator.


- Download the iPhone emulator and install your Mac. [iPhone Emulator Download](#).
- Use the Record and Analyze method from the Recording Wizard to create capture file.

## Recording with a Google Android Emulator


- If you are recording with Google Android Emulator Version 2.0 and above, apply the following workaround if you are experiencing problems recording:
  1. Enter a new Port Mapping by selecting **Recording Options > Network > Port Mapping** and select **New Entry**.
  2. Specify a Target server and port.



3. Enter a second Port Mapping entry without changing any details.




4. Disable the second entry so all traffic is handled by the first entry in the Port Mapping.

**Note:**

- This limitation was fixed in Google Android Emulator Version 4.03
- While recording a SSL site, you may encounter a warning message stating that there are

problems with the certificate for the site. Click continue to proceed with the recording.



## How to Create a Script by Analyzing Traffic

This task describes how to create a Vuser script using a network traffic file (capture file). You can use one of the following methods to create a capture file, or you can use one that you generated with an external tool such as Fiddler or Wireshark.

### 1. Create a capture file on a Windows Platform - optional

Create a capture file containing a log of all TCP traffic over the network on a Windows platform. Use a downloadable capture tool or use the tool provided in the product's bin folder, `lrcapdump.<platform>`.

- a. Run the capture utility in a command window `lrcapdump -f<file_name>.cap`. `lrcapdump` prompts you to select a network card.

- b. Type in the number of the interface card (if there are multiple ones.) and click Enter.
  - c. Perform typical actions within your application.
  - d. Return to the command window and click Enter to end the capture session.
  - e. Place the capture file on the network in a location accessible to the machine running VuGen.
2. **Create a capture file using HP's LoadRunner Mobile Recorder-optional**
- For details, see "[How to Record with the Mobile Recorder](#)" on page 708
3. **Create a capture file on a Linux Redhat Platform - optional**
- a. Copy the LinuxRH3 folder from LoadRunner installation disk **DVD\Additional Components\mobileRemoteAgent**, to the Linux machine.
  - b. Run the following commands in the shell to give the two files executable permissions on Linux.
    - i. `chmod +x mongoose`
    - ii. `chmod +x cgi-bin/mobileCGI.cgi`
  - c. Perform a **Change directory** to the **cgi-bin/** folder and run the following commands:
    - i. `export SCRIPT_FILENAME=<Full path of mobileCGI.cgi>`, where <Full path of mobileCGI.cgi> is the path to the mobileCGI.cgi file.
    - ii. `export QUERY_STRING=STARTRECORD=0`, where 0 is the 0-based sequence number of the network interface in VuGen's Start Recording dialog box.
    - iii. `./mobileCGI.cgi` This generates a **currentPCAP.pcap** file which contains all traffic captured over the specified Ethernet interface.

**Note:** Step iii is primarily for troubleshooting, to make sure that your Linux environment was configured correctly. Once verified, you do not need to run this command again in future runs.

- d. Run a Mongoose command with the following options:
- ```
mongoose -e errorLog.txt -r "/root/LinuxRH3" -C ".cgi" -p <port> , where
/root/LinuxRH3 is the path containing the mongoose file.
```

The `-p <port>` parameter represents the port that Mongoose listen on.

- e. Then you can connect from VuGen to this port.

#### 4. Create a capture file on a UNIX Platform - optional

Create a capture file containing all TCP traffic over the network on a UNIX platform.

- a. Locate the appropriate lrcpdump utility for your platform in the product's bin folder. Copy it to a folder that is accessible to your UNIX machine. For example, for an HP platform, copy lrcpdump.hp9. If using FTP, make sure to use the binary transfer mode.
- b. Switch to the root user to provide execution permissions: chmod 755 lrcpdump.<platform>
- c. If there are multiple interface cards, lrcpdump uses the first one in alphabetical order. To get a complete list of the interfaces, use the ifconfig command.
- d. Run the utility with its complete syntax, specifying the interface and file name. For example, **lrcpdump.hp9 -ieth0 -f<file\_name>.cap**. The capturing of the network traffic begins.
- e. Perform typical actions within your application.
- f. Return to the window running **lrcpdump** and follow the instructions on the screen to end the capture session.
- g. Place the capture file on the network in a location accessible to the machine running VuGen.

#### 5. Option 1 - Create a Script from within Windows Explorer

Select the **pcap**, **Ircap**, or **saz** (Fiddler) file in the Windows Explorer on the machine upon which VuGen is installed. Select **Create VuGen script** from the right -click menu. VuGen converts the capture file to a script and opens it in VuGen.

#### 6. Option 2 - Create a Script from within VuGen

- a. Click the **Start Record** button to start the recording wizard. Select the **Analyze Traffic** method.
- b. Browse to the capture file and specify the section of the script into which you want to load the traffic: *vuser\_init*, *Action*, or *vuser\_end*.
- c. Indicate whether you want to analyze server or client side traffic. For details, see "[Analyzing Traffic](#)" on page 698.
- d. To analyze traffic from a secure server, click the **SSL Configuration** button to add its certificates. For details, see "[SSL Configuration Dialog Box](#)" on page 877.

For details, see the "[Recording Wizard](#)" on page 709

**Note:** If you have load on the server that prevents getting responses on time, you can create a

script based on requests only by editing the registry.

Go to regedit and add a DWORD key to the below location:

Location:

Software\\Mercury Interactive\\LoadRunner\\Protocols\\HTTP\\Analyzer\\

Key:

AllowAutomaticOutApiEvents = 1

## **How to Record and Analyze a Script for Mobile Applications**

This task describes how to record and analyze a script with the Recording Wizard.

### **1. Prerequisites**

- If you are recording the capture file on a remote server, you must manually start the mobile sniffer agent.
- If you are recording the capture file on the local host, you must connect your mobile device to the local host.

For details, see "[Recording Traffic into a Capture \(Sniffer\) File](#)" on page 694.

### **2. Create new Mobile Application - HTTP/HTML script**

- a. Select **New script > Web - HTTP/HTML script**.
- b. Click the **Start Record** button.
- c. Select the **Record and Analyze** method.

For details, see "[Recording Wizard](#)" on page 709

### **3. Specify mobile sniffer agent location**

Enter the URL where the mobile sniffer agent resides. For example, if the mobile sniffer agent is on the local machine enter `http:\\localhost`.

### **4. Configure mobile sniffer agent**

- a. Specify the Record network interface. This is the network adapter to which you want the mobile sniffer agent to listen.
- b. Specify which section of the script into which you want to load the traffic: `vuser_init`, `Action`, or `vuser_end`.

### **5. Select Start Recording**

Record the desired business process.

## 6. Select Stop Recording

VuGen will generate the capture file.

Save capture file on the local machine when you are prompted.

## 7. Analyze Traffic

For details, see "[How to Create a Script by Analyzing Traffic](#)" on page [704](#) starting with Step 4.

# How to Record with the Mobile Recorder

This task describes how to create a .lrcap file of application traffic directly on your mobile Android device.

## 1. Prepare the mobile device for recording

- To use the LoadRunner Mobile Recorder, your mobile device must be **rooted**<sup>1</sup>.

**Note:** While rooting devices has been declared legal by the United States Copyright Office, in certain cases it may void the warranty. It is recommended that you use a specifically designated testing device.


- Download and install [LoadRunner Mobile Recorder](#).

## 2. Record business process

- From the home screen, tap the  icon to open the LoadRunner Mobile Recording


application.

- Tap the  button to begin the recording session.

**Note:** The  button switches to  button and a LoadRunner Mobile Recorder icon opens on the phone's notification bar.

- Press the device's home button to switch to the home screen.
- Open the application to record and perform the steps of the business process.

<sup>1</sup>The process of allowing privileged control to the device's subsystem.

- e. To stop the recording, either:
  - i. Press the home button and tap the  icon and tap the **Stop Recording** button to stop the recording session.
  - ii. or tap the LoadRunner Mobile Recorder icon in the notification bar and swipe the  notification. This automatically brings you to the LoadRunner Mobile Recorder home screen. Tap the **Stop Recording** button.

### 3. Export the recorded session

- a. Select a file to export.

You can send the default .lrcap file or tap  to select a previously recorded .lrcap file.

- b. Tap the  button to select an application:

- c. In the displayed window, select the application to which you want to export the file.

### 4. Create Vuser script

- a. Open the e-mail, download the .lrcap file, and then double-click it. VuGen automatically opens, creates and generates the script.

## Recording Wizard

This wizard enables you to configure record and analyze setting for the Mobile Application - HTTP/HTML protocol.

|                                                       |                                                                                                                                                                                                                                                                                                                   |
|-------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>To access</b>                                      | Click the <b>Start Record</b> button                                                                                                                                                                                                                                                                              |
| <b>Important information</b>                          | <a href="#">"Recording Traffic into a Capture (Sniffer) File" on page 694</a><br><a href="#">"Analyzing Traffic" on page 698</a>                                                                                                                                                                                  |
| <b>Wizard map:<br/>Record and<br/>Analyze Traffic</b> | <p>The following is the wizard map if you select Record and Analyze in the Recording Method page:</p> <p><a href="#">"Recording Method Dialog Box" on the next page</a> &gt; <a href="#">"Configure and Record Dialog Box" on page 711</a> &gt; <a href="#">"Analyze Traffic Dialog Box" on the next page</a></p> |
| <b>Wizard map:<br/>Analyze Traffic</b>                | <p>The following is the wizard map if you select Analyze Traffic in the Recording Method page:</p> <p><a href="#">"Recording Method Dialog Box" on the next page</a> &gt; <a href="#">"Analyze Traffic Dialog Box" on the next page</a></p>                                                                       |

|                                        |                                                                                                                                                                                                       |
|----------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Wizard map:<br/>Record Emulator</b> | The following is the wizard map if you select Record Emulator in the Recording Method page:<br><br><a href="#">"Recording Method Dialog Box" below &gt; "Record Emulation Dialog Box" on page 712</a> |
| <b>Wizard map: Proxy<br/>Recording</b> | The following is the wizard map if you select Proxy Recording in the Recording Method page:<br><br><a href="#">"Recording Method Dialog Box" below &gt; "Proxy Recording Dialog Box" on page 712</a>  |
| <b>Relevant tasks</b>                  | <a href="#">"How to Create a Script by Analyzing Traffic" on page 704</a><br><a href="#">"How to Record and Analyze a Script for Mobile Applications" on page 707</a>                                 |

## Recording Method Dialog Box

This dialog box enables you to select a recording method.

|                       |                                                                                                                                                                       |
|-----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>To access</b>      | <b>VuGen &gt; Start Record button</b>                                                                                                                                 |
| <b>Relevant tasks</b> | <a href="#">"How to Create a Script by Analyzing Traffic" on page 704</a><br><a href="#">"How to Record and Analyze a Script for Mobile Applications" on page 707</a> |

User interface elements are described below:

| UI Element                        | Description                                                                                                                                                              |
|-----------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Analyze Traffic</b>            | Create a script by converting an existing capture file to a Vuser script. For details, see <a href="#">"Recording Traffic into a Capture (Sniffer) File" on page 694</a> |
| <b>Record and Analyze Traffic</b> | Create a Vuser script by recording events with a device emulator installed on the VuGen machine.                                                                         |
| <b>Record Emulator</b>            | Create a Vuser script by recording events with a device emulator installed on the VuGen machine.                                                                         |
| <b>Proxy Recording</b>            | Create a Vuser script by recording a client application via the LoadRunner proxy.                                                                                        |

## Analyze Traffic Dialog Box

This dialog box enables you to configure settings for script generation from an existing capture file.

|                  |                                                                  |
|------------------|------------------------------------------------------------------|
| <b>To access</b> | <b>VuGen &gt; Recording Method &gt;Analyze Traffic &gt; Next</b> |
|------------------|------------------------------------------------------------------|

User interface elements are described below:

| UI Element                                                                                      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|-------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Capture file</b>                                                                             | <p>The name of a capture file containing the server traffic.</p> <p>VuGen supports capture files with the following extensions: .cap, .pcap, .lrcap, .saz.</p> <p>In addition, only files where the link-layer header type is either <code>LINKTYPE_ETHERNET</code> or <code>LINKTYPE_LINUX_SLL</code> are supported by VuGen. If your link-layer header is not one of the above, your file may not be parsed correctly.</p> <p>The link-layer header type can be determined by opening the capture file within Wireshark and selecting Statistics &gt; Summary &gt; Encapsulation from the main menu.</p> |
| <b>Browse</b>  | Allows you to select a capture file to import.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <b>Server side filter</b>                                                                       | <p>The IP address and port of the server whose traffic you want to examine. You can specify multiple servers.</p> <p>You can filter by both server and client side traffic.</p>                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <b>Client side filter</b>                                                                       | <p>The IP address of the client whose traffic you want to examine.</p> <p>You can filter by both server and client side traffic.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>Record into action</b>                                                                       | The section into which you want to record: vuser_init, Action, or vuser_end. For actions you want to repeat, use the Action section. For initialization steps, use vuser_init.                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <b>Filter options</b>                                                                           | Opens the Traffic Filters node in the Recording Options dialog box. This allows you to specify which IP addresses to include or exclude from the script during script generation.                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>SSL configuration</b>                                                                        | Opens the SSL Configuration Dialog Box which allows you to add SSL certificates to analyze traffic from a secure server.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

## Configure and Record Dialog Box

This dialog box enables you to configure settings to record traffic to a pcap file.

|                       |                                                                                                                                                                       |
|-----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>To access</b>      | <b>Recording Wizard &gt; Recording Method &gt; Next</b>                                                                                                               |
| <b>Relevant tasks</b> | <a href="#">"How to Create a Script by Analyzing Traffic" on page 704</a><br><a href="#">"How to Record and Analyze a Script for Mobile Applications" on page 707</a> |

User interface elements are described below:

| UI Element                           | Description                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Mobile sniffer agent location</b> | <b>Host URL.</b> URL where the mobile sniffer agent resides.<br><b>Port.</b> Specify the port for the mobile sniffer agent to listen.                                                                                                                                                                                                                                                                 |
| <b>Mobile sniffer configuration:</b> | <b>Record Network Interface.</b> Servers and computers can have multiple network adapters. The setting enables you to select the network adapter you want the mobile agent to listen on.<br><b>Record into Action.</b> The section into which you want to record: vuser_init, Action, or vuser_end. For actions you want to repeat, use the Action section. For initialization steps, use vuser_init. |
| <b>Recording</b>                     | <b>Start Recording.</b> Begin recording traffic.<br><b>Stop Recording: Stop recording traffic.</b>                                                                                                                                                                                                                                                                                                    |

## Record Emulation Dialog Box

This dialog box enables you to configure the settings to use a mobile emulator to record a script.


|                  |                                                         |
|------------------|---------------------------------------------------------|
| <b>To access</b> | <b>Recording Wizard &gt; Recording method &gt; Next</b> |
|------------------|---------------------------------------------------------|

User interface elements are described below:

| UI Element                   | Description                                                                                                                                                                               |
|------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Emulator to record</b>    | Specify the location of the emulator application executable.                                                                                                                              |
| <b>Command line</b>          | Specify the arguments that the emulator application requires to run the emulator.                                                                                                         |
| <b>Working directory</b>     | Specify the location of the of the emulator application.                                                                                                                                  |
| <b>Action to record into</b> | Specify the section into which you want to record: vuser_init, Action, or vuser_end.<br>For actions you want to repeat, use the Action section. For initialization steps, use vuser_init. |
| <b>Options button</b>        | Access the <b>Recording Options</b> pane.                                                                                                                                                 |

## Proxy Recording Dialog Box

This dialog box enables you to configure proxy settings.



|                              |                                                                   |
|------------------------------|-------------------------------------------------------------------|
| <b>To access</b>             | <b>VuGen &gt; Recording Method &gt; Proxy Recording &gt; Next</b> |
| <b>Important information</b> | <a href="#">"Recording via a Proxy- Overview" on page 260</a>     |
| <b>Relevant tasks</b>        | <a href="#">"How to Record a Script via a Proxy" on page 261</a>  |

User interface elements are described below:

| UI Element                                         | Description                                                                                      |
|----------------------------------------------------|--------------------------------------------------------------------------------------------------|
| <b>LoadRunner proxy listens on port:</b>           | Specify the port on which the LoadRunner proxy will listen, for example, Port 8080.              |
| <b>Display recording toolbar on client machine</b> | The recording toolbar enables you to control the recording of your script on the client machine. |

## LoadRunner Mobile Recording Application User Interface

This application enables you to record application traffic to a capture (.lrcap) file on your mobile android device.

|                  |                                                                                                                                |
|------------------|--------------------------------------------------------------------------------------------------------------------------------|
| <b>To access</b> | Tap the  icon from your device home screen. |
|------------------|--------------------------------------------------------------------------------------------------------------------------------|

|                              |                                                                                                                                                                                  |
|------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Important information</b> | <ul style="list-style-type: none"> <li>Your mobile device must be <b>rooted</b><sup>1</sup>.</li> <li>Download and install <a href="#">LoadRunner Mobile Recorder</a></li> </ul> |
| <b>Relevant tasks</b>        | <a href="#">"How to Record with the Mobile Recorder" on page 708</a>                                                                                                             |

## Home Screen

| UI Element                                                                                               | Description                                                         |
|----------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------|
| <b>Record business process</b>                                                                           |                                                                     |
|  <b>Start Recording</b> | <b>Start Recording.</b> Begin a recording session.                  |
|  <b>Stop Recording</b>  | <b>Stop Recording.</b> End a recording session.                     |
| <b>Send recorded session</b>                                                                             |                                                                     |
|  ...                    | <b>Browse.</b> Browse to select a previously recorded session.      |
| <i>Send to:</i><br><input type="text" value="John.Doe@gmail.com"/>                                       | <b>Send to.</b> Specify an e-mail address to send the file.         |
|  <b>Export</b>        | <b>Send.</b> Send the .lrcap file to the designated e-mail address. |

## Advanced options

| UI Element                                                         | Description                                                                                                                                                        |
|--------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Email Settings</b>                                              |                                                                                                                                                                    |
| <input type="checkbox"/> <i>Send automatically after recording</i> | Option to send .lrcap file to designated email after  button has been tapped. |

<sup>1</sup>The process of allowing privileged control to the device's subsystem.

| UI Element                                                                                                                            | Description                                                                                                                                    |
|---------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <input type="checkbox"/> <i>Delete files automatically after sending</i>                                                              | Option to delete .lrcap file after  button has been tapped. |
| <b>Working folder</b>                                                                                                                 |                                                                                                                                                |
| <i>Capture files are saved to this location</i><br> | Option to select a folder on the device to save the .lrcap file.                                                                               |
|                                                      | Browse to the folder to save the .lrcap file.                                                                                                  |

## Mobile TruClient

### ***Mobile TruClient Protocol***

Based on LoadRunner's innovative TruClient technology, TruClient Ajax - Mobile enables you to test web applications designed for mobile devices.

With this protocol you can:

- Simulate various mobile browsers.
- Develop scripts that are recorded on the user level making them clear and easily maintained.

The following illustrates the workflow for using the Mobile TruClient protocol:



### ***How to Record a Script with Mobile TruClient***

1. Create a new  Mobile TruClient script
2. Select  button

Define mobile device, user agent and display size in the Mobile Settings Dialog Box which opens automatically.

For details, see "[Mobile TruClient Device Manager Dialog Box](#)" below.

### 3. Record business process

For details on using TruClient's functionality, see [Ajax TruClient Protocol](#).

## **How to Add, Remove, and Import Mobile Device Settings for Mobile TruClient**

### **How to Create a Custom Device Using the Mobile Device Manager**

The TruClient Ajax - Mobile device manager is delivered with the settings for many popular mobile devices, however, you can easily add a custom device.

1. Click the TruClient Ajax - MobileDevice Manager from the VuGen toolbar.
2. Select **Add Mobile Device**. This opens the **Add Mobile Device** dialog box.
3. Enter the name of the device you would like to add or select an existing device from the drop-down list to customize.
4. Specify the User Agent. For details, see "[Mobile TruClient Device Manager Dialog Box](#)" below.
5. Specify the Display. For details, see "[Mobile TruClient Device Manager Dialog Box](#)" below.

### **How to Remove a Mobile Device**

1. Click the TruClient Ajax - MobileDevice Manager from the VuGen toolbar.
2. Select Remove Mobile Device. This opens the Remove Mobile Device dialog box.
3. Highlight the unwanted device and click remove.

### **How to Import a Mobile Device Settings to Your Script**

The import feature can be used to import mobile devices created in other users' scripts.

1. Open a script that contains custom device settings.
2. Click the TruClient Ajax - MobileDevice Manager from the VuGen toolbar.
3. Select the **Import Device Settings**. This opens the **Import Device Settings** dialog box.
4. Highlight the custom device and select import.

## **Mobile TruClient Device Manager Dialog Box**

This utility enables you to configure, add and import mobile device settings that are used with the TruClient Ajax - Mobile Protocol.

|                       |                                                                                                                                                                                                                                                                                                                                                                                       |
|-----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>To access</b>      | Use one of the following: <ul style="list-style-type: none"><li>• <b>Script development</b> button </li><li>• <b>Tools &gt; Mobile TruClient Device Manager</b></li><li>• <b>Mobile Settings</b> button </li></ul> |
| <b>Relevant tasks</b> | <a href="#">"How to Add, Remove, and Import Mobile Device Settings for Mobile TruClient" on the previous page</a><br><a href="#">"How to Record a Script with Mobile TruClient" on page 715</a>                                                                                                                                                                                       |

| UI Element           | Description                                                                                                                                                                                          |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Mobile Device</b> | Select the mobile device type you want to test.                                                                                                                                                      |
| <b>User Agent</b>    | Specify the header string that is sent to server to identify your mobile device. Once you have selected a device, the default header value will appear. However, this header string can be modified. |
| <b>Display</b>       | Specify the height and width of your mobile device screen. Mobile TruClient will open browser window according to the display settings.                                                              |

## SAP Mobile Platform

### ***How to create an SMP (SAP Mobile Platform) script***

The SMP (SAP Mobile Platform) protocol enables you to create and replay .Net based scripts using files that have been generated by SMP, formerly known as SUP. This task describes the steps to create an SMP script.

#### **Prerequisites**

To create an SMP script you will need to record a business process with SMP, a platform that is provided by Sybase, an SAP company. The recording generates the following files:

- Action.cs
- Vuser\_init.cs
- Vuser\_end.cs

#### **Create an SMP (SAP mobile Platform) script**

1. Select **New Script and Solution > SMP (SAP Mobile Platform)**.
2. Copy the generated .cs files (described in "[How to create an SMP \(SAP Mobile Platform\) script](#)" on the previous page) into the script folder.

**Note:** The recording mechanism for SMP scripts is disabled.

3. Save, close and reopen the script.
4. Update the location of the SAP.Mobile.LoadRunner.dll from **Run-Time Settings > .Net > Shared DLLs**.

**Note:** The SAP.Mobile.LoadRunner.dll has been developed and is maintained by Sybase, an SAP company.

5. Generated .cs files can include objects from external .dlls. To successfully replay the script, include a reference to these .dlls in **Run-Time Settings > .Net > Shared DLLs**
6. Replay the script. For details, see "[Debugging .NET Vuser Scripts](#)" on page 726.

## .NET Protocol

### .NET Protocol Overview

Microsoft .NET Framework provides a foundation for developers to build various types of applications such as ASP.NET, Windows Forms, Web Services, distributed applications, and applications that combine several of these models.

VuGen supports .NET as an application level protocol. VuGen allows you to create Vuser scripts that emulate users of Microsoft .NET client applications created in its .NET Framework. VuGen records all of the client actions through methods and classes, and creates Vuser scripts in C Sharp or VB .NET.

By default, the VuGen environment is configured for .NET Remoting, ADO.NET, Enterprise Services, and WCF (Windows Communication Foundation) applications. Contact Customer Support for information on how to configure VuGen to record applications created with other client-server activity.

### ***Considerations for Working with the .NET Protocol***

The .NET protocol enables you to load test by replaying the application's method calls.

You can write a load test script manually, or you can generate a load test script by recording a business process.

Unlike other LoadRunner transport based protocols, the .NET protocol records the application method calls that are specified in the filter. Method calls that are not defined in the filter are not included in the generated script during the recording of the application.

Typically, a user is able to generate a script that can be used for load test using the default environment filter. However, for certain complex applications it may be difficult to generate a working script because the wrong method has been specified in the filter. The most difficult task of creating a load test script with the .NET protocol is resolving recording or code generation errors.

The following requirements will facilitate your ability to define the correct filter for the recording process and generate a working load test script:

- You should be familiar with .NET framework.
- You should be able to code using C# or VB.NET.
- You should be familiar with XML.
- You should have Visual Studio 2010 installed.
- You should have an understanding of the architecture and communication techniques of the application so as to determine what functions or classes are relevant for the load test script.

The following can streamline the process of creating the correct filter:

You should have access to the application code or have some .NET reflector tools to enable you to view the decompiled code.

You should have access to the developers of the application who can help you identify the methods that are required for the load test.

For more information about .NET and the above environments, see the [MSDN Web site](#).

## Viewing Data Sets and Grids

When you record a method returning a dataset, data table, or data reader action, VuGen generates a grid for displaying the data.

When working with a data reader, VuGen collects the data retrieved from each **Read** operation and converts it to the replay helper function, **DoDataRead**.

For example, after recording the following application code,

```
SqlDataReader reader = command.ExecuteReader();
while( reader.Read() )
{
    // read the values, e.g., get the string located in column 1
    string str = reader.GetString(1)
}
```

VuGen generates the following lines in the script:

```
SqlDataReader_1 = SqlCommand_1.ExecuteReader();
LrReplayUtils.DoDataRead(SqlDataReader_1, out valueTable_1, true, 27);
```

where the two parameters indicate that during recording, the Application read all 27 available records. Therefore, during replay the script will read all available records.

In addition, VuGen generates a data grid containing all the information retrieved by the **Read** operations.

During replay you can use the output data table, containing the actual retrieved values, for correlation and verification. For more information regarding the **DoDataRead** function, see the Function Reference (**Help > Function Reference**).

When applicable, VuGen displays grid steps in the Step Navigator, and displays the associated grids in the Snapshot pane.

| Data of RECORDSET_XML(5) |               |                    |           |             |                  |             |                |
|--------------------------|---------------|--------------------|-----------|-------------|------------------|-------------|----------------|
|                          | FLIGHT NUMBER | DEPARTURE INITIALS | DEPARTURE | DAY OF WEEK | ARRIVAL INITIALS | ARRIVAL     | DEPARTURE TIME |
| 1                        | 5709          | DEN                | Denver    | Saturday    | LAX              | Los Angeles | 05:21 PM       |
| 2                        | 3636          | DEN                | Denver    | Saturday    | LAX              | Los Angeles | 01:45 PM       |
| 3                        |               |                    |           |             |                  |             |                |
| 4                        |               |                    |           |             |                  |             |                |
| 5                        |               |                    |           |             |                  |             |                |
| 6                        |               |                    |           |             |                  |             |                |
| 7                        |               |                    |           |             |                  |             |                |
| 8                        |               |                    |           |             |                  |             |                |
| 9                        |               |                    |           |             |                  |             |                |

The dataset is stored in an XML file. You can view this XML file in the script's data/datasets folder. The data files are represented by an `<index_name>.xml` file, such as `20.xml`. Since one file may contain several data tables, see the file **datasets.grd**, which maps the script index to the file index to determine which XML contains the data.

## Recording WCF Duplex Communication

WCF (Windows Communication Foundation) is a programming model that unifies Web Services, .NET Remoting, Distributed Transactions, and Message Queues into a single Service-oriented programming model for distributed computing.

WCF creates a proxy object to provide data for the service. It also marshalls the data returned by the service into the form expected by the caller.


In addition to general support for the WCF environment, VuGen provides specialized support for applications that use WCF's duplex communication. In duplex communication, the client proxy contacts the service, and the service invokes the callback handler on the client machine. The callback handler implements a callback interface defined by the server. The server does not have to respond in a synchronous manner—it independently determines when to respond and invoke the callback handler.

### Communication Between Client and Server

The communication between the client and server is as follows:

- The server defines the service contract and an interface for the callback.

- The client implements the callback interface defined by the server.
- The server calls the callback handler in the client whenever needed.



When trying to record and replay duplex communication, you may encounter problems when the script calls the original callback methods. By default, the callback handlers are not included in the filter. You could customize the filter to include those callback handlers. However, the standard playback would be ineffective for a load test, since many of the callbacks are local operations such as GUI updates. For an effective load test you cannot replay the original callback method invoked by the server.

VuGen's solution is based on replacing the original callback handler with a dummy implementation. This implementation performs a typical set of actions that you can customize further for your application.

You instruct VuGen to replace the original callbacks by activating the **Generate Dummy Callback Handler** recording option. For more information, see "[".NET > Recording - Recording Node](#)" on page 221.

### **VuGen Implementation of a Duplex Callback**

As part of the duplex communication solution, VuGen generates two support files:

- `DuplexCallbackHelper.<language>`
- `Callback_Name.<language>`

The following example shows the generated files for a Calculator application using duplex communication:

```

namespace Script
{
    using System;
    using System.Threading;
    using System.ServiceModel;
    using System.Collections.Generic;
    using Mercury.LoadRunner.DotNetProtocol.Replacement;

    //-----  

    // Helper class for handling duplex callbacks  

    // This class is the base class for the dummy  

    // used when "Generate dummy callback handler"  

    public class vuserDuplexcallbackHelper<ID, RE>
    {
        // Initialize LoadRunner API
        protected LoadRunner.LrApi lr = new LoadRunner.LrApi();

        // Synchronization event for responses
        private AutoResetEvent waitForResponseEvent = new AutoResetEvent(false);
    }
}

```

The Helper file serves as a general template for working with duplex callback handlers. It serves as a base class for the implementation of the callback.

The second file, **Callback\_Name**, contains the implementation of the callback. The name of the callback implementation class is **Vuser<xxxx>** where xxxx is the name of the callback interface and it inherits from the **VuserDuplexCallbackHelper** class defined in the Helper file. VuGen creates separate implementation files for each interface.

This file performs two primary tasks:

**Set Response.** It stores the data that came from the server in a map. It stores them with sequential IDs facilitating their retrieval. This method is called from the implementation of the callback interface. The following sample code demonstrates the dummy implementation of a callback method named **Result**. The method's arguments are stored in the map as an object array.

```

// -----
public virtual void Result(string operation, double result) {
    // Add here your own callback implementation and set the response data
    SetResponse(responseIndex++, new object[] {
        operation,
        result});
}

```

- **Get Response.** Waits for the next response to arrive. The implementation of **GetNextResponse** retrieves the next response stored in the map using a sequential indexer, or waits until the next response arrives.

The script calls **GetNextResponse** at the point that the original callback handler was called during recording. At that point, the script prints a warning:

```

// Wait here for the next response.
// The original callback during record was:

```

## **Replacement of the Callback in the Script**

When you enable the **Dummy Callback** option (enabled by default), VuGen replaces the original duplex callback handlers with dummy implementations. The dummy implementation is called Vuser <Callback Name>. At the point of the original callback handler, the script prints a warning indicating that it was replaced.

### **Customizing the Dummy Implementation**

You can modify the implementation file to reflect your environment. This section contains several suggested customizations.

#### Timeouts

The default timeout for which the callback waits for the next response is 60000 msec, or one minute. To use a specific timeout, replace the call to **GetNextResponse** with the overloading method which gets the timeout as an argument as shown below. This method is implemented in the callback implementation file <Callback\_Name> listed in the left pane after the **DuplexCallbackHelper** file.

```
// Get the next response.
    // This method waits until receiving the response from the server
    // or when the specified timeout is exceeded.
    public virtual object GetNextResponse(int millisecondsTimeout) {
        return base.GetResponse(requestIndex++, millisecondsTimeout);
    }
```

To change the default threshold for all callbacks, modify the **DuplexCallbackHelper** file.

```
// Default timeout threshold while waiting for response
protected int millisecondsTimeoutThreshold = 60000;
```

#### Key Identifier

Many applications assign key identifiers to the data, which connects the request and response to one another. This allows you to retrieve the data from the map using its ID instead of the built-in incremental index. To use a key identifier instead of the index, modify the file <Callback\_Name> replacing the first base template parameter, **named ID**, with the type of your key identifier. For example, if your key identifier is a string you may change the first template argument from **int** to **string**:

```
public class VuserXXX : VuserDuplexCallbackHelper<string, object>
```

In addition, you may remove the implementation of **GetNextResponse()** and replace it with calls to **GetResponse(ID)** defined in the base class.

#### Return Values

By default, since VuGen supports **OneWay** communication, the implementation callback does not return any value or update an output parameter when it is invoked.

```
public virtual void Result(string operation, double result) {
    // Add here your own callback implementation and set the response da
ta
```

If your application requires that the callback return a value, insert your implementation at that point.

#### Get Response Order

In VuGen's implementation, a blocking method waits for each response. This reflects the order of events as they occurred during recording—the server responded with data. You can modify this behavior to execute without waiting for a response or to implement the blocking only after the completion of the business process.

#### Find Port

The **FindPort** method in the Helper file is a useful utility that can be used in a variety of implementations. The Helper class uses this method to find unique ports for running multiple instances of the script. You can utilize this utility method for other custom implementations.

### Recording Server Hosted By Client Applications

If the communication in your system is a server hosted by a client, VuGen's default solution for duplex communication will not be effective. In server hosted by client environments, it is not true duplex communication since the client opens the service and does not communicate through the Framework. For example, in queuing, the client sends a message to the service and opens a response queue to gather the responses.

To emulate a server hosted by a client, use the pattern depicted in the above solution—replace the original response queues with dummy callbacks and perform synchronization as required. For more information, contact HP support.

## Asynchronous Calls

When VuGen records asynchronous calls on remote objects, you can specify how the calls are handled in the [".NET > Recording - Recording Node"](#) on page 221. These options are particularly relevant for .NET Remoting and WCF environments.

You can configure VuGen to one of the following options:

- **Call original callbacks by default.** Uses the recorded application's original callback when generating and replaying the script. If the callback method is explicitly excluded by a filter, the callback will be excluded even if you enable this option. If your callbacks perform actions that are not directly related to the business process, such as updating the GUI, then make sure to disable this option.
- **Generate asynchronous callbacks.** This option defines how VuGen will handle callbacks when the original callbacks are not recorded. This is relevant when the above option, **Call original callbacks** is disabled or when the callbacks are explicitly excluded.

When you enable this option, it creates a dummy method which will be called during replay instead of the original callback. This dummy callback will be generated in the **callbacks.cs** section of the script.

When you disable this option, VuGen inserts a NULL value for the callback and records the events as they occur.

The following segment shows script generation for a Calculator client, when **Generate asynchronous callbacks** is enabled.

To display the callback method, OnComplete1, you click on the **callback.cs** file in the left pane.

The following segment shows script generation when the option is disabled. VuGen generates a NULL in place of the callback and records the events of the callback as they occur.

**Note:** If you recorded a script with specific recording options, and you want to modify them, you do not need to re-record the script. Instead you can regenerate the script with the new settings.

For more information, see ".NET > Recording - Recording Node" on page 221.

## Recording Dual HTTP Bindings

If your application employs dual HTTP Binding, since HTTP is inherently not a duplex protocol, the framework uses a standard port to receive response data being passed to the callback. When you attempt to run multiple instances of your application, you may be unable to do so using the same port number. VuGen provides you with an option of replacing the original client base address's port number with a unique port.

When you enable the **Generate Unique Client Base Address** recording option, VuGen checks the type of communication used by the application. If it detects dual HTTP communication, **WSDualHttpBinding**, it runs the **FindPort** utility (provided in LrReplayUtils) in the Helper file and finds unique ports for each instance of the callback.

This option is enabled by default. It is only relevant when you enable the above option, **Generate dummy callback handler**.

When you enable this option, VuGen generates the following code in the script:

```
#warning: Code Generation Warning
// Override the original client base address with a unique port number
DualProxyHelper.SetUniqueClientBaseAddress<XXXX>(YYYYYY);
```

For more information, see ".NET > Recording - Recording Node" on page 221.

## Connection Pooling

ADO.NET providers deploy a feature called **connection pooling** which can significantly influence load test accuracy. Whenever only one app domain is used for all Vusers, connection pooling is turned on—.NET Framework keeps the database connections open and tries to reuse them when a new connection is requested. Since many Vusers are executed in the context of a single application domain, they may interfere with one another. Their behavior will not be linear and that may decrease their accuracy.

In the .NET run-time settings, the AppDomain Per Vuser property enables execution of each Vuser in a separate app domain (true by default). This means that there is connection pooling in the scope of each Vuser, but the Vusers will not interfere with one another. This setting provides more accuracy, but lower scalability.

If you disable this option, you need to manually disable connection pooling for the database.

The following table describes how to manually disable connection pooling:

| Provider                                         | Option                                                                                                                                                                                                                                                                                                                       |
|--------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| .NET Framework Data Provider for SQL Server      | "Pooling=false" or "Pooling=no"                                                                                                                                                                                                                                                                                              |
| .NET Framework Data Provider for Oracle          | "Pooling=false" or "Pooling=no"                                                                                                                                                                                                                                                                                              |
| .NET Framework Data Provider for ODBC            | Connection pooling is managed by an ODBC Driver Manager. To enable or disable connection pooling, use the ODBC Data Source Administrator (found in Control Panel or the Administrative Tools folder). The Connection Pooling tab allows you to specify connection pooling parameters for each of the installed ODBC drivers. |
| .NET Framework Data Provider for OLE DB          | "OLE DB Services=-2"                                                                                                                                                                                                                                                                                                         |
| Oracle Data Provider for .NET                    | "Pooling=false"                                                                                                                                                                                                                                                                                                              |
| Adaptive Server Enterprise ADO.NET Data Provider | "Pooling=False"                                                                                                                                                                                                                                                                                                              |

## Debugging .NET Vuser Scripts

You can compile a .NET Vuser script to check its syntax, without running the script. To compile the script directly from VuGen, press Shift+F5 or select **Vuser > Compile**. If VuGen detects a compilation error, it displays the error in the Output window. Double-click on the error to go to the problematic line in the script.

To run the script directly from VuGen, press F5 or select **Replay > Run**. Breakpoints and step-by-step replay are not supported in VuGen's editor window for .NET Vusers. To debug a script and run it with breakpoints or step-by-step, run it from within Visual Studio .NET as described below.

## Viewing Scripts in Visual Studio

Visual Studio provides you with additional tools to view, edit, and debug your Vuser scripts. You can add breakpoints, view variable values, add assembly references, and edit the script using Visual Studio's IntelliSense. You can also run the script in a step-by-step mode for debugging.

When you save your script, VuGen creates a Visual Studio 2010 solution file, **Script.sln**, in your script's folder. You can open the solution file in Visual Studio .NET and view all of its components in the Solution Explorer.

To open the Vuser script in Visual Studio 2010, select **Design > Open Script in Visual Studio** or click the **Visual Studio** button  on the VuGen toolbar.

**Note:**

- If the Vuser script was created with an earlier version of LoadRunner (11 or earlier), LoadRunner will open the script in Visual Studio 2008.
- If Visual Studio 2010 is also installed, the script will be converted to a Visual Studio 2010 solution.
- If the script was created with LoadRunner 11.50 or later, it requires Visual Studio 2010.

Double-click the appropriate section in the Solution Explorer, such as **vuser\_init.cs**, to view the contents of the script.

**Note:** Note that VuGen automatically loads all of the necessary references that were required during recording. You can add additional references for use during compilation and replay through the Solution Explorer. Select the **Reference** node and select **Add Reference** from the right-click menu.

Click on **globals.cs** or **globals.vb** in the Solution Explorer to view a list of the variables defined and used by your script.

## .NET Filters Overview

Recording filters indicate which assemblies, interfaces, namespaces, classes, or methods to include or exclude during the recording and script generation.

By default, VuGen provides built-in system filters for .NET Remoting, ADO.NET, Enterprise Services, and WCF (Windows Communication Foundation). These filters were designed to include the relevant interfaces for standard ADO.NET, Remoting, Enterprise Services, and WCF. VuGen also allows you to design custom filters.


Custom filters provide several benefits:

- **Remoting.** When working with .NET Remoting, it is important to include certain classes that

allow you to record the arguments passed to the remote method.

- **Missing Objects.** If your recorded script did not record a specific object within your application, you can use a filter to include the missing interface, class or method.
- **Debugging.** If you receive an error, but you are unsure of its origin, you can use filters to exclude methods, classes, or interfaces in order to pin-point the problematic operation.
- **Maintainability.** You can record script in higher level, make script more easy to maintain and to correlate.

A filter manager lets you manipulate existing custom filters. It displays the assemblies, namespaces, classes, methods, and properties in a color-coded tree hierarchy.



The bottom pane provides a description of the assembly, namespace, class, method, property, or event. It also indicates whether or not it is included or excluded and a reason for the inclusion or exclusion.

## .NET Filters - Advanced

In the Filter Manager's tree hierarchy, it only displays public classes and methods. It does not show non-public classes or delegates.

You can add classes or methods that are not public by manually entering them in the filter's definition file.

The filter definition files, <filter\_name>.xml reside in the dat\DotnetFilters folder of your installation. The available Action properties for each element are: **Include**, **Exclude**, or **Totally Exclude**. For more information, see "["Filter Manager \[.NET Protocol\]" on page 216](#)".

By default, when you exclude a **class**, the Filter Manager applies **Exclude**, excluding the class, but including activity generated by the excluded class. When you exclude a **method**, however, it applies **Totally Exclude**, excluding all referenced methods.

```

<Assembly Name="mercury.vugen.dotnetsharedservices"
  Action="Exclude" />
</Assemblies>
- <Filter>
  - <Namespace Name="System" Action="Default">
    - <Namespace Name="Data" Action="Exclude"
      Environment="ADO.NET">
      - <Namespace Name="Common" Action="Default">
        - <Class Name="DataAdapter" Action="Include">
          <Method
            Name="get_AcceptChangesDuringFill"
            Action="TotallyExclude" />
          <Method Name="get_Container"
            Action="TotallyExclude" />
          <Method
            Name="get_ContinueUpdateOnError"
            Action="TotallyExclude" />
        <Method

```

For example, suppose Function A calls function B. If Function A is **Excluded**, then when the service calls Function A, the script will include a call to Function B. However, if function A is **Totally Excluded**, the script will not include a call to Function B. Function B would only be recorded if called directly—not through Function A.

VuGen saves a backup copy of the filter as it was configured during the recording, **RecordingFilterFile.xml**, in the script's **data** folder. This is useful if you made changes to the filter since your last recording and you need to reconstruct the environment.

## Guidelines for Setting .NET Filters

When testing your .NET application, your goal is to determine how the server reacts to requests from the client. When load testing, you want to see how the server responds to a load of multiple users.

When recording a .NET application, your script may include calls to methods that do not affect the server, such as calls to a local utility or the GUI interface. These calls are usually not relevant to your testing goals, and it would be correct to filter them out.

The built-in filters, .NET Remoting, ADO.NET, Enterprise Services, and WCF, were designed to record only the server related traffic relevant to your testing goals. In some instances, however, you

may need to customize filters to capture your .NET application's calls or exclude unnecessary calls. Using the Filter Manager, you can design custom filters to exclude the irrelevant calls and capture the server related calls.

Before creating a test, we recommend that you become familiar with your application and determine its primary classes and methods, so that you will know which ones to include in your recording.

If you are not familiar with your application's classes, you can use **Visual Studio** or a **Stack Trace** to help you determine which methods are being called by your application in order to include them in the filter. VuGen allows you to record with a stack trace that logs all of the methods that were called by your application.

Once you determine the required methods and classes, you include them using the Filter Manager. When preparing a script, you may need to customize the filter several times in order to achieve the optimal filter. An optimal filter records the relevant methods without introducing a large number of irrelevant calls to the script.

**Tip:** Strive to modify the filter so that your script will compile (Shift+F5) inside VuGen—a test with correct syntax. Then customize the filter further to create a functional script that runs inside VuGen.

Note that if you plan to add manual code to your script such as control flow or message statements, make sure to do so after you have a functional script that runs inside VuGen. The reason for this is that if you re-record a script or regenerate the script, you will lose all of the manual changes.

## Determining which Elements to Include or Exclude

When designing a custom filter, we recommend that you start by choosing the appropriate built-in filter as a base filter. You can then customize the filter using one of the following approaches:

- **Top Down Approach.** An approach in which you include the relevant namespace and exclude specific classes that are not part of the client-server activity. This is recommended if you are familiar with your application and you can identify a well-defined assembly which implements all client-server activity without involving any GUI elements, such as MyDataAccessLayer.dll.
- **Bottom up Approach.** An approach in which you use the default filter and refine it by adding individual methods or classes. Use this approach if you cannot identify a well-defined layer or if you are not familiar with your application. Do not add all AUT assemblies and then try to remove extra component one by one.

The following section provides guidelines on when to include or exclude elements.

- If, as a result of your including a class, your script has many unrelated method calls, try modifying the filter to exclude the irrelevant methods.
- If you identify a non-client/server call in your script, exclude its method in the filter.
- During recording, VuGen may detect an unknown input argument, for example, an argument whose construction it had never encountered before. If this argument supports serialization, VuGen **serializes** it by saving it to a file in a special format. During replay, VuGen reconstructs

the argument by **deserializing** it.

- VuGen serializes objects passed as arguments that were not included by the filter. We recommend that you include this object in the filter in order to track its construction and activity instead of using it in its serialized form. You can identify serialized objects in the script by searching for calls to the **LrReplayUtils.GetSerializedObject** method or, in WCF environments, **LrReplayUtils.GetSerializedDataContract**. VuGen stores serialized objects in the script's **\data\SerializedObjects** folder as XML files with indexes: **Serialization\_1.xml**, **Serialization\_2.xml** and so forth.
- When no rules are specified for a method, it is excluded by default. However, when the remoting environment is enabled, all remote calls are included by default, even if they are not explicitly included. To change the default behavior, you can add a custom rule to exclude specific calls which are targeted to the remote server.
- Arguments passed in remoting calls whose types are not included by the filter, are handled by the serialization mechanism. To prevent the arguments from being serialized, you can explicitly include such types in order to record the construction and the activity of the arguments.
- Exclude all activity which involves GUI elements.
- Add assemblies for utilities that may be required for the script to be compiled.

For information on how to include and exclude elements, see "["Filter Manager \[.NET Protocol\]" on page 216](#).

## Defining an Effective Filter

When preparing a script, you may need to customize the filter several times in order to achieve the optimal filter. An optimal filter records the relevant methods without introducing a large number of irrelevant calls to the script.

### Define an Effective Filter

1. Create a new filter based on one of the built-in filters. If you know that the AUT (Application Under Test) does not use ADO.NET, Remoting, WCF, or Enterprise Services, clear that option since unnecessary filters may slow down the recording.
2. Set the **Stack Trace** option to true for both recording and code generation. Open the Recording Options (ctrl+f7) and select the **Recording** node. Enable **Debug Options: Stack Trace** and **Code Generation: Show Stack Trace**.
3. Record your application. Click **Start Record** (ctrl + r) to begin and Stop (ctrl + f5) to end.
4. View the script's steps. If you can determine the business logic from the steps and apply correlation, you may not need to create custom filters. If, however, the script is very long or hard to maintain or correlate, you should customize the script's filter.
5. Try to identify the high-level method in the call that captures or wraps one or more client server calls. You can do this by opening the AUT source files (if they are available) in Visual Studio or

by viewing a Stack Trace of the script.

6. Set the filter to include the relevant methods—you may need to add their assembly beforehand. For tips about including and excluding elements in the filter, see "[".NET Filters Overview" on page 727](#).
7. Record the application again. You should always re-record the application after modifying the filter.
8. Repeat steps 4 through 7 until you get a simple script which can be maintained and correlated.
9. After creating an optimal script, turn off the **Stack Trace** options and regenerate the script. Open the Recording Options (ctrl+f7) and select the **Recording** node. Disable **Debug Options: Stack Trace and Code Generation: Show Stack Trace**. This will improve the performance of subsequent recordings.
10. Correlate the script. In order for your test to run properly, you may need to insert a correlation to capture a value and use it at a later point in the script. For more information, see "[How to Correlate Scripts - Microsoft .NET" on page 294](#).

## How to Configure Application Security and Permissions

A Security Exception that occurs while recording an application is usually due to a lack of permissions—the recording machine does not have sufficient permissions to record the application. This is common where your application is not local, but on the Intranet or network.

To solve this problem, you need to allow the recording machine to access the application and the script with Full Trust.

One solution is to copy the application and save your script locally, since by default, users have Full Trust permissions to all local applications and folders.

An additional solution is to create new code groups that gives Full Trust to each application folder, and the script folder.

### Grant Full Trust permissions to a Specific Folder (Visual Studio NOT installed)

1. From the command prompt, run the caspol.exe application.
2. Set the desired permission.

### Grant Full Trust Permissions to a Specific Folder (Visual Studio installed)

1. Open the .NET Configuration settings. Select **Start > All Programs > Administrative Tools > Microsoft .NET Framework 2.0 Configuration**. The .NET Configuration window opens.
2. Expand the **Runtime Security Policy** node to show the Code Groups of the machine.

3. Select the **All\_Code** node.
4. Select **Action > New**. The Create New Code Group dialog box opens.
5. Enter a name for a new Code Group for your application or script. Click **Next**.
6. Select the **URL** condition type. In the URL box, specify the full path of the application or script in the format `file://...` and click **Next**.
7. Select the **FullTrust** permission set. Click **Next**.
8. Click **Finish** in the Completing the Wizard dialog box. The configuration tool adds your Code Group to the list of existing groups.
9. Repeat the above procedure for all .NET applications that you plan to record.
10. Repeat the above procedure for the Vuser script folder.

**Note:** Make sure that the script folder has **FullTrust** permissions on all Load Generator machines that are participating in the test (LoadRunner only).

## .NET - Troubleshooting and Limitations

This section describes troubleshooting and limitations for .NET Vuser scripts.

The following limitations apply to the VuGen recording of a Microsoft .NET application:

- .NET Vuser scripts support only single-protocol recording in VuGen.
- Direct access to public fields is not supported—the AUT must access fields through methods or properties.
- VuGen does not record static fields in the applications—it only records methods within classes.
- Multi-threaded support is dependent on the client application. If the recorded application supports multi-threading, then the Vuser script will also support multi-threading.
- In certain cases, you may be unable to run multiple iterations without modifying the script. Objects that are already initialized from a previous iteration, cannot be reinitialized. Therefore, to run multiple iterations, make sure to close all of the open connections or remoting channels at the end of each iteration.
- Recording is not supported for Enterprise Services communication based on MSMQ and Enterprise Services hosted in IIS.
- VuGen partially supports the recording of WCF services hosted by the client application.

- Recording is not supported for Remoting calls using a custom proxy.
- Recording is not supported for **ExtendedProperties** property of ADO.NET objects, when using the default ADO.NET filter.
- Applications created with .NET Framework 1.1 which are not compatible with Framework 2.0, cannot be recorded. To check if your Framework 1.1 application is compatible, add the following XML tags to your application's .config file:

```
<configuration>
  <startup>
    <supportedRuntime version="v2.0.50727"/>
  </startup>
</configuration>
```

Invoke the application (without VuGen) and test its functionality. If the application works properly, VuGen can record it. Remove the above tags before recording the AUT with VuGen. For more information regarding this solution, see the MSDN Knowledge Base.


- Applications that use the .NET Remoting Framework and are executed in CLR 2 (.NET frameworks 2/3/3.5), might crash during recording. During a crash you will receive a message containing the strings Version=4.x.x.x, and "is not registered for activation".  
**Potential Workaround:** In the Microsoft .NET: Recording user interface under Support for previous.NET version, select **Emulate previous .NET versions in transport level**, and then record again.
- When the application under test retrieves a server-activated object by calling new RemoteObject(), VuGen generates a RemotingServices.Connect function.
- Applications using multiple processes or multiple application domains are only partially supported.
- Shared DLLs must be specified in the Recording Options only. Changes made in the Run-Time Settings to the list of shared DLLs have no effect.

## Oracle NCA Protocol

### Oracle NCA Protocol Overview

Oracle NCA is a protocol that handles communication with the Oracle Forms server. Using your browser, you launch the database client, an applet viewer. You perform actions on the NCA database through its applet viewer. This eliminates the need for client software and allows you to perform database actions from all platforms that support the applet viewer.

The NCA environment is a three-tier environment. The user first sends an http call from his browser to a Web server. This call accesses the startup HTML page which invokes the Oracle Applications applet. The client (applet viewer) communicates through the proprietary NCA protocol with the application server (Oracle Forms server) which then submits information to the database server.



VuGen records and replays the NCA communication between the client and the Forms server (application server).

The Oracle NCA protocol is commonly used as a multi-protocol in combination with Web (HTTP/HTML). This is the recommended way to record with Oracle NCA. If you are using Oracle NCA as a single protocol, web events are recorded but steps are not generated (or replayed) by default.

If you initially created a single protocol script for Oracle NCA, and at a later stage you require the Web functions for testing, you can regenerate your script in VuGen to add the Web functions, without having to re-record the session. You indicate this from the Protocols node in the Recording Options.

## Oracle NCA Protocol Example Scripts

In the following example, the user selected an item from a list (**nca\_list\_activate\_item**), pressed a button (**nca\_button\_press**), retrieved a list value (**nca\_lov\_retrieve\_items**), and performed a click in an edit field (**nca\_edit\_click**). The logical names of the objects are the parameters of these functions.

```
...
nca_lov_select_item("Responsibilities", "General Ledger, Vision Operations");
nca_list_activate_item("FNDSCSGN.NAVIGATOR.LIST.0", "+ Journals");
nca_list_activate_item("FNDSCSGN.NAVIGATOR.LIST.0", "      Enter");
nca_button_press("GLXJEENT.TOOLBAR.LIST.0");
nca_lov_find_value("Batches", "");
nca_lov_retrieve_items("Batches", 1, 9);
nca_lov_select_item("Batches", "AR 1020 Receivables 2537: A 1020");
nca_edit_click("GLXJEENT.FOLDER_QF.BATCH_NAME.0");
...

```

In certain tests, such as those performed on Oracle Configurator applications, information returned by one function is required throughout the session. VuGen automatically saves the dynamic information to a parameter, by inserting a **web\_reg\_save\_param** function into the script. In the following example, the connection information is saved to a parameter called NCAJServSessionID.

```
web_reg_save_param ("NCAJServSessionId", "LB=\r\n\r\n", "RB=\r",
LAST);
web_url("f60servlet",
```

```
"URL=http://ussciforms05.sfb.na/servlet/f60servlet?\?config
=mult",           LAST);
```

In the above example, the right boundary is \r. The actual right boundary may differ between systems.

**Note:** We recommend that the user not modify the **web\_reg\_save\_param** parameters if they were generated automatically. Alternatively, you can manually add a new **web\_reg\_save\_param** function or add a new correlation rule.

## Oracle NCA Record and Replay Tips

When recording an Oracle NCA Vuser script, follow these guidelines:

- We recommend installing Jinitiator before recording a script.
- Close all browsers before you begin recording.
- Record the login procedure in the **vuser\_init** section. Record a typical business process in the Actions section. When you run the script, you can then specify multiple iterations for a specific business process. For more information, see "["Solution Explorer - Overview" on page 80](#)".
- VuGen supports the recording of Oracle Forms applications using the Forms Listener Servlet in multi-protocol mode. The application server uses the **Forms Listener Servlet** to create a runtime process for each client. The runtime process, **Forms Server Runtime**, maintains a persistent connection with the client and sends information to and from the server.

To support Forms 4.5 in replay, modify the **mdrv\_oracle\_nca.dat** file in the **dat > mdrv** folder to match the following example:

```
[Oracle_NCA]
ExtPriorityType=protocol
WINNT_EXT_LIBS=ncarp110.dll
WIN95_EXT_LIBS=ncarp110.dll
LINUX_EXT_LIBS=liboranca.so
SOLARIS_EXT_LIBS=liboranca.so
HPUX_EXT_LIBS=liboranca.sl
AIX_EXT_LIBS=liboranca.so
LibCfgFunc=oracle_gui_configure
UtilityExt=lrun_api
```

To restore Forms support for versions later than 4.5, restore the original values.

## Pragma Mode

The client side of the Oracle NCA Vuser can be configured to send an additional header to the server named **Pragma**. The header is a counter that behaves in the following way: the initial message of the NCA handshake has a value of 1.

The messages that follow the handshake are counted, beginning with 3. The counter is incremented by 1 for each message sent by the client.

If the message received from the server is the type `plain\text` and the body of the message begins with `ifError:#/#00`, the client sends a 0 byte message to the server and the Pragma value changes its sign to a minus. This sign changes back after the client succeeds in receiving the information from the server.

Recording of the Pragma header is only supported in the multi-protocol mode (Oracle NCA and Web). You can identify the Pragma mode within the script's default.cfg file. When operating in Pragma mode, the UseServletMode is set to 2.

```
[HttpConnectMode]
UseHttpConnectMode=1
RelativeURL=<NCAJServSessionId>
UseServletMode=2
```

For information on the Pragma related run-time settings, see "["Oracle NCA > Client Emulation Node" on page 371.](#)

To identify the Pragma mode, you can perform a WinSock level recording and check the buffer contents. In the first example, the buffer contains the Pragma values as a counter:

```
send buf108
    "POST /ss2servlet/oracle.forms.servlet.ListenerServlet?JServSessionIdss2ser"
    "vlet=gk5q79uqy1 HTTP/1.1\r\n"
    "Pragma: 1\r\n"
    ...
send buf110
    "POST /ss2servlet/oracle.forms.servlet.ListenerServlet?JServSessionIdss2ser"
    "vlet=gk5q79uqy1 HTTP/1.1\r\n"
    "Pragma: 3\r\n"
    ...
```

In the following example, the buffer contains the Pragma values as an error indicator:

```
recv buf129 281
    "HTTP/1.1 200 OK\r\n"
    "Date: Tue, 21 May 2002 00:03:48 GMT\r\n"
    "Server: Oracle HTTP Server Powered by Apache/1.3.19 (Unix) mod_fastcgi/2.2"
    ".10 mod_perl/1.25 mod_oreocmigr/1.0\r\n"
    "Content-Length: 13\r\n"
    "Content-Type: text/plain\r\n"
    "\r\n"
    "ifError:8/100"
send buf130
    "POST /ss2servlet/oracle.forms.servlet.ListenerServlet?JServSessionIdss2ser"
    "vlet=gk5q79uqy1 HTTP/1.1\r\n"
    "Pragma: -12\r\n"
    ...
```

# How to Enable the Recording of Objects by Name

When recording an Oracle NCA script, you must record the session using object names instead of the standard object ID. If the script is recorded using the object ID, replay may fail because the ID is generated dynamically by the server and may differ between iterations. You can verify that your script is being recorded with object names by examining the **nca\_connect\_server** function.

```
nca_connect_server("199.35.107.119","9002"/*version=11i*/,"module=/d1/oracle
    /visappl/fnd/11.5.0/forms/US/FNDSCSGN userid=APPLSYSPUB/PUB@VIS
    fndnam=apps record=names");
```

If the **record=names** argument does not appear in the **nca\_connect\_server** function, you may be recording object IDs. You can instruct VuGen to record object names by modifying one of the following:

## Startup HTML File

If you have access to the startup HTML file, you instruct VuGen to record object names instead of its object ID by setting the **record=names** flag in the startup file, the file that is loaded when you start the Oracle NCA application. The following steps describe how to enable the recording of object names using the startup HTML file.

1. Edit the startup file that is called when the applet viewer begins by modifying the line shown below.

```
<PARAM name="serverArgs ... fndnam=APPS">
```

2. Add the Oracle key **record=names** as shown below.

```
<PARAM name="serverArgs ... fndnam=APPS record=names">
```

## Forms Configuration File

If the application has a startup HTML file that references a Forms Web CGI configuration file **formsweb.cfg** (a common reference), you may encounter problems if you add **record=names** to the Startup file. In this situation, you should modify the configuration file. The following steps describe how to enable the recording of object names using the configuration file.

1. Go to the Forms Web CGI configuration file.
2. Define a new parameter in this file (see sample Web CGI configuration file below for this change).

```
serverApp=forecast
serverPort=9001
serverHost=easgdev1.dats.ml.com
connectMode=socket
archive=f60web.jar
archive_ie=f60all.cab
xrecord=names
```

3. Open the startup HTML file and locate PARAM NAME="serverArgs".
4. Add the variable name as an argument to the ServerArgs parameter, for example, record=%xrecord% as shown below.

```
<PARAM NAME="serverArgs" VALUE="module=%form% userid=%userid% %otherParams% record=%xrecord%">
```

5. Alternatively, you can edit the **basejini.htm** file in the Oracle Forms installation folder. This file is the default HTML file for running a form on the web using JInitiator-style tags to include the Forms applet. In the basejini.htm file add the following line to the parameter definitions:

```
<PARAM NAME="recordFileName" VALUE="%recordFileName%">
```

In the <EMBED> tag, add the following line:


```
serverApp="%serverApp%"  
logo="%logo%"  
imageBase="%imageBase%"  
formsMessageListener="%formsMessageListener%"  
recordFileName="%recordFileName%"
```

The drawback in editing this file instead of the servlet configuration file **formsweb.cfg**, is that this file is replaced when you reinstall Oracle Forms. To avoid this, you can create a copy of the **basejini.htm** file and store it at another location. In the servlet configuration file, edit the **baseHTMLJinitiator** parameter to point to the new file.

## URL to Record

If you do not have access to the startup HTML file, you can still have Oracle NCA record object names instead of its object ID by modifying the URL to record. The following solution only works if the startup HTML file does not reference another file while loading.

For this solution, you add "?record=names" after the URL in the Start Recording dialog box, after the URL name to record.



# How to Launch Oracle Applications via the Personal Home Page

When launching Oracle Forms applications (versions 6i and higher) by logging in through the **Personal Home Page**, you must set several system profile options at the user level. It is desirable to pass such variables at the user level, and not at the site level, where it will affect all users. The following steps describe how to configure the "ICX: Forms Launcher" profile.

1. Sign on to the application and select the "System Administrator" responsibility.
2. Select **Profile/System** from the Navigator menu.
3. Within the **Find System Profile Values** form:
  - a. Select the **Display > Site** option
  - b. **Users** = <your user logon> for example, operations, mfg, and so on)
  - c. **Enter Profile** =%ICX%Launch%
  - d. Click **Find**.
4. Update the User value to the **ICX:Forms Launcher** profile:
  - If no parameter has been passed to the URL, append the following string to the end of the URL of the user value: ?play==;record=names
  - If a parameter has been passed to the URL, append the following string to the end of the URL of the user value: =;play==;record=names
5. Save the transaction.
6. Log out of the Oracle Forms session.
7. Log out of the Personal Home Page session.
8. Sign on again via the **Personal Home Page** using your username.

If you were unable to update the ICX: Forms Launcher profile option at the user level, open the **Application Developer** responsibility and select the **Updatable** option for the **ICX\_FORMS\_LAUNCHER** profile.

The first parameter passed to the URL must begin with a question mark (?). You pass all subsequent parameters with an ampersand (=;). In most cases, the URL already contains parameters, which you can identify by searching for a question mark.

## Oracle NCA - Troubleshooting and Limitations

This section describes troubleshooting and limitations for Oracle NCA protocol scripts.

## Testing Secure Oracle NCA Applications

- In the Port Mapping node of the Recording Options dialog box, delete any existing entries for port 443 and create a new entry for the Oracle server name:

**Service ID:** HTTP

**Target Server:** Oracle Forms Server IP address or long host name

**Target Port:** 443

**Connection Type:** SSL

**SSL Version:** Active SSL version. If in doubt, select SSL 2/3.

Note that the **Service ID** is **HTTP** and not **NCA**.

For more information, see "[Network > Port Mapping Node](#)" on page 226.

- If you encounter problems when replaying an NCA HTTPS script during the **nca\_connect\_server** command, insert the following function at the beginning of the script.


```
web_set_sockets_option("SSL_VERSION", "3");
```

## Testing Servlets and other Oracle NCA Applications

Certain NCA sessions use servlets:

- the Forms Listener servlet
- applications or modules that use both NCA and HTTP communications, such as the Oracle Configurator
- the initializing of the NCA application (downloading the applet, jar, and gif files)

When recording servlets, you must record both Oracle NCA and Web functions. You can do this by using the Oracle Apps Ili protocol or creating an Oracle NCA multi-protocol script. Alternatively, if you created a single protocol script for Oracle NCA, open the **General > Protocols** node in the Recording Options, and enable the Web protocol. Then you can begin recording.



If you are unsure whether your application uses servlets, you can check the **default.cfg** file in the script folder after recording a script. Locate the entry "**UseServletMode=**"

If the value is 1 or 2, then servlets are being used and you must enable HTTP recording in addition to Oracle NCA.

If you already recorded a script, you can regenerate the code automatically to include the Web functions without having to re-record. Select **Record > Regenerate Script**, and select the Web protocol in the Protocols section.

## Determining the Recording Mode

When recording Oracle NCA scripts: VuGen automatically determines the correct connection mode: HTTP or Socket mode. Generally, you are not required to modify any of the recording settings as VuGen auto-detects the system configuration (unless you are working with Forms Server 4.5). In systems where the standard port mapping are reserved by other applications, you may need to modify the Port Mapping settings, depending on the recording mode.

You can determine the recording mode in one of the following ways:

- When using the NCA application, open the Java Console.

```
proxyHost=null
proxyPort=0
connectMode=HTTP
Forms Applet version is: 60812
```

The **connectMode** entry indicates **HTTP**, **HTTPS**, or **socket**.

- After recording an NCA session, open the **default.cfg** file in the Vuser folder and check the value of the **UseHttpConnectMode** entry.

```
[HttpConnectMode]
UseHttpConnectMode= 2
// 0 = socket 1 = http 2 = https
```

When defining a new port mapping in the Server Entry dialog box, use a **Service ID** of **HTTP** for **HTTP** or **HTTPS** modes. For **Socket** mode, use a **Service ID** of **NCA**.

For more information about Port Mapping settings, see "["Network > Port Mapping Node" on page 226](#)".

## Recording Trace Information for Oracle DB

To debug your script, you can use the Oracle DB breakdown graphs. To gather data for this graph, you turn on the trace mechanism before running the script.

To manually turn on the tracing mechanism, use the **nca\_set\_custom\_dbtrace** function. For more information, see the Function Reference ([Help > Function Reference](#)).

# RDP Protocol

# RDP Protocol - Overview

**Note:** This topic applies to RDP Vuser scripts only.

The Microsoft RDP (Remote Desktop Protocol) enables one computer [the client] to connect to another computer [the server] over a network connection. For example, you can use RDP to connect to a central, powerful server for working on specific business applications or graphic terminals. This provides you with the same look and feel as if you are working on a standalone PC. The client computer employs RDP client software for this purpose, while the other computer must run RDP server software. The client software is referred to as **Remote Desktop Connection**. The server software is referred to as **Remote Desktop Services**.

For details on the versions of RDP that are supported by VuGen, see the LoadRunner Product Availability Matrix (PAM).

**Note:** RDP versions 5.1 and later have an **Experience** tab that allows you to set various options. This tab is not supported by VuGen recording. All options are set to the ON position.

## RDP Recording Tips

**Note:** This topic applies to RDP Vuser scripts only.

When recording an RDP Vuser script, follow these guidelines in order to create an effective script.

### Single vs. Multi-Protocol Scripts

When creating a new script, you may create a single protocol or multi-protocol script. For example, to record both RDP traffic and Web responses, create a multi-protocol script for RDP and Web to enable the recording of both protocols.

### Record into Appropriate Sections

Record the connection process into the **vuser\_init** section, and the closing process into the **vuser\_end** section. This will prevent you from performing iterations on the connecting and disconnecting processes. For more information about recording into sections, see "["Solution Explorer - Overview"](#) on page 80.

### Run a Clean Session

When recording a session, make sure to perform the complete business process, starting with the connection and ending with the cleanup. End your session at a point from where you could start the entire process from the beginning. Do not leave any client or application windows open.

You should also configure your terminal server to end disconnected sessions. Select **Administrative Tools > Terminal Services Configuration > Connection Properties > Sessions > Override User Settings** and set the server to end disconnected sessions.

## Explicit Mouse Clicks

When opening expanded menu options, click explicitly on each option—do not depend on the expanding menu. For example, when choosing **Start > All Programs > Microsoft Word**, be sure to click on the word **Programs**.

## Using Windows Logo key combinations

**Note:** This tip applies only to Windows 8 installations on remote computers.


Because support for mouse movement in RDP Vusers can cause performance issues, by default, mouse movement support is disabled. Therefore, when you record an RDP Vuser script, it is recommended that you use the **Windows Logo** key combinations to display the Start screen [Windows Logo key], to show the Desktop [Windows logo key + D], and to open the charms bar [Windows Logo key + C].

When you run an RDP Vuser script, Windows key combinations can be applied either on the host computer or on the remote computer. To ensure that Windows key combinations are applied on the remote computer, when you record the connection to the remote computer, you must specify that Windows key combinations are applied on the remote computer.

How to apply Windows key combinations on the remote computer

1. Open the Remote Desktop Connection dialog box.
2. Click **Options** to expand the dialog box.
3. Click the **Local Resources** tab.
4. Under **Keyboard**, from the **Apply Windows key combinations** list, select **On the remote**

computer.



## Synchronizing using Windows 8 apps

**Note:** This tip applies only to Windows 8 installations on remote computers.

Because many Windows 8 apps have dynamic user interfaces, avoid using these apps for image-based synchronization.

## Working with Clipboard Data (RDP Protocol)

**Note:** This topic applies to RDP Vuser scripts only.

VuGen allows you to copy and paste the text of a clipboard during an RDP session. You can copy the contents locally and paste them remotely, or vice versa—copy the contents from the remote machine and paste them locally. The copying of text is supported in TEXT, LOCALE, and UNICODE formats.

VuGen generates separate functions when copying or saving the clipboard data.

### **Code sample #1**

The following example illustrates a copy operation on a local machine and a paste operation on a remote machine:

```
//Notifies the Remote Desktop that new data is available in the Local machine's
//clipboard. The data can be provided in three formats: TEXT, UNICODE and LOCALE
rdp_notify_new_clipboard_data(
    "StepDescription=Send local clipboard formats 1",
    "Snapshot=snapshot1.inf",
    "FormatsList=RDP_CF_TEXT|RDP_CF_UNICODE|RDP_CF_LOCALE",
    RDP_LAST );
rdp_key(
    "StepDescription=Key Press 2",
    "Snapshot=snapshot_9.inf",
    "KeyValue=V",
    "KeyModifier=CONTROL_KEY",
    RDP_LAST );
//Provides clipboard data to the Remote Desktop when it requests the data.
rdp_send_clipboard_data(
    "StepDescription=Set Remote Desktop clipboard 1",
    "Snapshot=snapshot1.inf",
    "Timeout=20",
    REQUEST_RESPONSE, "Format=RDP_CF_UNICODE", "Text=text for clipboard",
    RDP_LAST );
```

### **Code sample #2**

This example illustrates a copy operation on a remote machine and a paste operation on a local machine:

```
rdp_key(
    "StepDescription=Key Press 2",
    "Snapshot=snapshot_9.inf",
    "KeyValue=C",
    "KeyModifier=CONTROL_KEY",
    RDP_LAST );
// The function requests the Remote Desktop UNICODE text and saves it to a //parameter
rdp_receive_clipboard_data(
    "StepDescription=Get Remote Desktop clipboard 1",
    "Snapshot=snapshot1.inf",
    "ClipboardDataFormat=RDP_CF_UNICODE",
    "ParamToSaveData=MyParam",
    RDP_LAST );
```

Normally, the Remote Desktop clipboard data is saved in UNICODE format. If the Remote Desktop requests data in the TEXT or LOCALE formats, the **rdp\_send\_clipboard\_data** function automatically converts the content of MyParam from UNICODE into the requested format and sends it to the Remote Desktop. The Replay log indicates this conversion with an informational message. If the conversion is not possible, the step fails.

For more information about the rdp functions, see the Function Reference (**Help > Function Reference**).

## Correlating Clipboard Parameters

During a recording session, if the client sends the server the same data that it received, VuGen replaces the sent data with a parameter during code generation. VuGen performs this correlation only when the received and sent data formats are the same.

### Code sample #3

The following example shows how the same parameter, **MyParam**, is used for both receiving and sending the data.

```
// Receive the data from the server
rdp_receive_clipboard_data("StepDescription=Get Remote Desktop clipboard 1",
"Snapshot=snapshot_9.inf",
"Timeout=0",
"ClipboardDataFormat=RDP_CF_UNICODETEXT",
"ParamToSaveData=MyParam",
RDP_LAST);
...
// Send the data to the server
rdp_send_clipboard_data("StepDescription=Get Remote Desktop clipboard 1",
"Snapshot=snapshot_9.inf",
"Timeout=10",
REQUEST_RESPONSE, "Format=RDP_CF_UNICODETEXT", "Text={MyParam}",
RDP_LAST);
```

## RDP Snapshots - Overview

**Note:** This topic applies to RDP Vuser scripts only.

Vuser scripts based on the RDP protocol utilize VuGen's Snapshot pane.

- For an introduction to the Snapshot pane, see "[Snapshot Pane - Overview](#)" on page 85.
- For details on how to work with the Snapshot pane, see "[How to Work with Snapshots](#)" on page 88.
- For details on the Snapshot pane UI, see "[Snapshot Pane](#)" on page 126.

When you open an RDP Vuser script, VuGen's standard Snapshot pane functionality is available. The Snapshot pane displays snapshots of the remote display, saved during recording and playback

of the Vuser script. Typically, these snapshots are used to synchronize playback of the Vuser script.

In addition to the basic Snapshot pane functionality, the Snapshot pane for RDP Vuser scripts lets you display snapshots in one of the following views:

- **Image.** Displays only the image of the snapshot and is ideal for visually comparing two images. This view displays the snapshot faster and requires less memory than the Full view. You can synchronize two snapshots in the Snapshot pane if both snapshots are displayed in the Image view. The Image view does not automatically scroll to show the area of a snapshot that is used for synchronization.
- **Full.** Scrolls to display the area that is used for synchronization. This view displays the snapshot slower and requires more memory than the Image view. You cannot synchronize two snapshots displayed in the Snapshot pane if either of the snapshots is displayed in the Full view. By default, snapshots are displayed in the Full view.

To display a specific synchronization snapshot in the Snapshot pane, do one of the following:

- In the Editor, select the step that contains a reference to the snapshot.
- In the Step Navigator, double-click the step that contains a reference to the snapshot.

When working with RDP Vuser scripts, the Snapshot pane lets you copy a snapshot to the clipboard, and display a snapshot of the most recent replay error. For more information on how to use the Snapshot pane, see "[How to Work with Snapshots](#)" on page 88.

## Image Synchronization Overview

**Note:** This topic applies to RDP Vuser scripts only.

An RDP session executes remotely. All keyboard and mouse handling is done on the server, and it is the server that reacts to them. For example, when you double-click an application on the desktop, it is the server that realizes a double-click took place and that the application must be loaded and displayed.

When an RDP client connects to a server, it does two things:

- It sends the server coordinates of actions. For example, 'clicked the left mouse button at coordinates (100, 100) on the screen'.
- It receives images from the server showing the current status of the screen after the action took place

The RDP client (and therefore, LoadRunner) does not know that the screen contains windows, buttons, icons, or other objects. It only knows the screen contains an image and at what coordinates the user performed the action. To allow the server to correctly interpret the actions, you set synchronization points within the script. These points instruct the script to wait until the screen on the server matches the stored screen before continuing.

The next time you replay the script, it will wait until the image returned by the server matches the image you selected.

## Image Synchronization Tips (RDP Protocol)


**Note:** This topic applies to RDP Vuser scripts only.

Use the following guidelines for effective image synchronization:


### Synchronize on the Smallest Significant Area

When synchronizing on an image, try to synchronize only the part of the image that is necessary. Additional details within the image may not be reproduced during replay and could result in a synchronization failure.

For example, when synchronizing on an image of a button, select only the text itself and not the dotted lines around the text as they may not appear during replay.



When synchronizing a highlighted area, try to capture only the part of the image that is not effected by the highlighting. In the following example, perform a synchronization on the Log Off icon, but not the entire button, since the highlighting may not appear during replay, and the color could vary with different color schemes.



### Synchronize Before Every User Action

It is recommended that you synchronize before every mouse operation. You should also synchronize before the first **rdp\_key** or **rdp\_type** operation that follows a mouse operation.

# Image Synchronization - Shifted Coordinates (RDP Protocol)

**Note:** This topic applies to RDP Vuser scripts only.

When replaying a script, a recorded object may appear at different coordinates on the screen. The object is the same, but its placement has been shifted. For example, during recording a window opened at coordinates (100, 100), but during replay at (200, 250).

In this case, the synchronization point will automatically find the new coordinates without any intervention on your part. It will automatically note the difference of 100 pixels in the horizontal axis and 150 pixels in the vertical axis.

All subsequent mouse operations that are coordinate dependent will use the modified coordinates, so that a mouse click recorded at (130, 130) will be replayed to (230, 280) = (130 + 100, 130 + 150).

You control the shifting of the coordinates through the **AddOffsetToInput** parameter in the **rdp\_sync\_on\_image** step. You can override this parameter to either add or not add the differences in location during replay to the recorded coordinates for any further operations. If you do not override this parameter, VuGen takes its value from the default setting in the run-time settings.

The corresponding parameter in the operations (for example **rdp\_mouse\_click** or **rdp\_mouse\_drag**) is **Origin**. This parameter decides whether the operation should take its coordinates only from the 'clean' values that were recorded, or whether it should take into account the differences that were added by the last synchronization point. If not explicitly specified, VuGen takes the value for this parameter from the run-time settings.

## Setting Security Levels in RDP Vuser Scripts


**Note:** This topic applies to RDP Vuser scripts only.

Remote Desktop Protocol (RDP) enables a client computer to connect to a server. Various security options are available for the connection, depending on the particular Windows operating systems that are installed on the client and server computers. The security options define security-related issues, such as the authentication and encryption, that are used for the connection.

The list of security options that are available for a Vuser script is different when you record a Vuser script and when you replay the script.

### Security levels when recording an RDP Vuser Script

Standard RDP security is the only form of security that you can use when you record an RDP Vuser script. Before you record an RDP Vuser script, make sure that the server is configured to allow connections from computers that are running any version of Remote Desktop, and not only from computers that are running Remote Desktop with Network Level Authentication. You use the **Remote** tab in the System Properties dialog box on the server to set the security level that is required to establish the connection.



### Security levels when replaying an RDP Vuser Script

You can use the Vuser script's run-time settings to specify the security that is used for the connection when the Vuser runs. The available security levels are:


- **RDP:** Connects using standard RDP security. RDP provides the least secure connection.
- **SSL:** Connects using SSL as an external security protocol to enhance the standard RDP security. SSL provides a moderate level of security.
- **CredSSP:** Connects using the Credential Security Support Provider (CredSSP) protocol. CredSSP provides the most secure connection.

**Note:** If you specify CredSSP authentication, you must make certain changes to the Vuser script each time the script is regenerated. For details, see [Modifying a script to support CredSSP authentication](#) below.

The security level that you specify in the run-time settings is an indication to the server of the maximum level of security that is supported by the client. However, the security that is actually used for the connection is defined by the server settings. For example, if you specify CredSSP as

the encryption level in the run-time settings, when you run the Vuser, the Vuser will inform the server that the Vuser supports CredSSP, SSL, and RDP security. If the server supports only RDP security (for example, its operating system is Windows 2003), then the connection will be made using RDP.


To set the RDP security level for the Vuser script, click **Replay > Run-Time Settings > RDP > Configuration** and then select the required level from the **Supported Encryption Level** list.



### Modifying a script to support CredSSP authentication

If you specify CredSSP authentication in the Vuser script's run-time settings, you must perform the following tasks each time the script is regenerated:

1. In the **rdp\_connect\_server** step in the script, modify the step to provide the user name, password, and domain that are required to access the server. For details on the **rdp\_connect\_server** step, see the Function Reference (**Help > Function Reference**).



2. Remove the block of code that contains the login-related mouse, keyboard, and image synchronization steps from the generated script, as described below.

- Locate the **rdp\_connect\_server** step in the Vuser script.

The step after the **rdp\_connect\_server** step is the first step in the block of code to delete.

- Locate the **rdp\_mouse\_click** step or the **rdp\_key** step that submits the password to the server.

This is the last step in the block of code to delete.

**Note:** If an **rdp\_set\_lock** step exists immediately after the **rdp\_connect\_server** step, do not delete the **rdp\_set\_lock** step.

- Delete all the steps in the block of code that is defined above.

```

vuser_init()
{
    rdp_connect_server("Host=Host1",
        "UserName=John",
        "EncryptedPassword=$0ee8de5e",
        "Domain=Domain1",
        RDP_LAST);

    rdp_set_lock("StepDescription=Lock Key Set 1",
        "LockKeyValue=VK_NUMLOCK",
        RDP_LAST);

    lr_think_time(12);

    rdp_sync_on_image("StepDescription=Image Synchronization 1",
        "WaitFor=Appear",
        "AddOffsetToInput=Default",
        IMAGEDATA,
        "ImageLeft=644", "ImageTop=562", "ImageWidth=40", "ImageHeight=40", "ImageName=snapshot_2.png", ENDIMAGE,
        RDP_LAST);

    rdp_mouse_click("StepDescription=Mouse Click 1",
        "Snapshot=snapshot_1.inf",
        "MouseX=664",
        "MouseY=582",
        "MouseButton=LEFT_BUTTON",
        "Origin=Default",
        RDP_LAST);

    rdp_type("StepDescription=Typed Text 1",
        "Snapshot=snapshot_3.inf",
        "TypedKeys=Password1",
        RDP_LAST);

    lr_think_time(11);

    rdp_sync_on_image("StepDescription=Image Synchronization 2",
        "WaitFor=Appear",
        "AddOffsetToInput=Default",
        IMAGEDATA,
        "ImageLeft=958", "ImageTop=616", "ImageWidth=40", "ImageHeight=40", "ImageName=snapshot_5.png", ENDIMAGE,
        RDP_LAST);

    rdp_mouse_click("StepDescription=Mouse Click 2",
        "Snapshot=snapshot_4.inf",
        "MouseX=978",
        "MouseY=636",
        "MouseButton=LEFT_BUTTON",
        "Origin=Default",
        RDP_LAST);
}

```

## RDP Agent (Agent for Microsoft Terminal Server) Overview

**Note:** This topic applies to RDP Vuser scripts only.

The Agent for Microsoft Terminal Server is an optional utility that you can install on the RDP server. It provides enhancements to the normal RDP functionality. It is provided in the LoadRunner installation DVD and you can install it on any RDP server. The agent provides you with more

intuitive and readable scripts, built-in synchronization, and detailed information about relevant objects. Note that when you run RDP Vusers with the agent installed, each Vuser runs its own process of Irrdpagent.exe. This results in a slight reduction in the number of Vusers that can run on the server machine.

## Tips for Using the Agent for Microsoft Terminal Server

- When opening application menus (e.g. File, Edit...) with the mouse, sync steps will sometimes fail. To avoid this issue, use the keyboard to select menu items when recording.
- When you add a **sync\_on\_object\_mouse\_click** step manually, the coordinates given are absolute coordinates (relating to the entire screen). To create the synchronization point, you need to calculate the offset in the window (relative coordinates) of the desired click location and modify the absolute coordinates accordingly for the synchronization to successfully replay.
- If a synchronization object exists at the correct location and time during replay, but is covered by another window (such as a pop-up), then the synchronization step will pass and a click will be executed on the window which is covering the synchronization point and therefore harm the script flow.
- During recording, if you want to return the application window to the foreground, either click on the title bar, or use the keyboard (ALT+TAB). Note that if you click inside the application window to return it to the foreground, the RDP session may terminate unexpectedly.

The Agent for Microsoft Terminal Server provides the following enhancements to the normal RDP functionality:

### Object Detail Recording

When the Agent for Microsoft Terminal Server is installed, VuGen can record specific information about the object that is being used instead of general information about the action. For example, VuGen generates **sync\_object\_mouse\_click** and **sync\_object\_mouse\_double\_click** steps instead of **mouse\_click** and **mouse\_double\_click** that it generates without the agent.

The following example shows a double-mouse-click action recorded with and without the agent installation. Note that with the agent, VuGen generates sync\_object functions for all of the mouse actions.

```
rdp_sync_object_mouse_double_click("StepDescription=Mouse Double Click on Synchronized Object 1",
    "Snapshot=snapshot_12.inf",
    "WindowTitle=RDP2",
    "Attribute=TEXT",
    "Value=button1",
    "MouseX=100",
    "MouseY=71",
    "MouseButton=LEFT_BUTTON",
    RDP_LAST);
rdp_mouse_double_click("StepDescription=Mouse Double Click 1",
    "Snapshot=snapshot_2.inf",
    "MouseX=268",
    "MouseY=592",
```

```
"MouseButton=LEFT_BUTTON",
"Origin=Default",
RDP_LAST);
```

## Expanded Right-Click Menu

When you click within a snapshot, you can insert several functions into the script using the right-click menu. When the agent is not active, you are limited to inserting only **mouse\_click**, **mouse\_double\_click**, and **sync\_on\_Image** steps. When the agent is installed, you are able to insert all possible steps that involve the RDP agent:

- **get\_object\_info** and **Sync\_on\_object\_info**. Provides information about the state of the object, and synchronize on a specific object property such as: ENABLED, FOCUSED, CONTROL\_ID, ITEM\_TEXT, TEXT, CHECKED, and LINES.
- **insert\_sync\_on\_text** and **get\_text**. For details, see the Function Reference (**Help > Function Reference**).

## Code sample

In the following example, the **rdp\_sync\_on\_object\_info** function provides synchronization by waiting for the Internet Options dialog box to come into focus.

```
rdp_sync_on_object_info("StepDescription=Sync on Object Info 0",
    "Snapshot=snapshot_30.inf",
    "WindowTitle=Internet Options",
    "ObjectX=172",
    "ObjectY=155",
    "Attribute=FOCUSSED",
    "Value={valueParam}",
    "Timeout=10",
    "FailStepIfNotFound=No",
    RDP_LAST);
```

## How to Install / Uninstall the RDP Agent

**Note:** This topic applies to RDP Vuser scripts only.

The installation file for the Agent for Microsoft Terminal Server is located on the LoadRunner installation disk, under the **Additional Components\ Agent for Microsoft Terminal Server** folder.

Note that the agent should be installed on your RDP server machine only, not on Load Generator machines.

If you are upgrading the agent, make sure to uninstall the previous version before installing the new one (see uninstallation instructions below).

## Install the RDP Agent

1. If your server requires administrator permissions to install software, log in as an administrator to the server.
2. Locate the installation file, **Setup.exe**, on the LoadRunner DVD in the **Additional Components\ Agent for Microsoft Terminal Server** folder.
3. Follow the installation wizard to completion.

To use the agent, you must set the recording options before recording a Vuser script. In the Start Recording dialog box, click **Options**. In the Advanced Code Generation node, select the **Use RDP Agent** check box.

## Uninstall the RDP Agent

1. If your server requires administrator privileges to remove software, log in to the server as an administrator.
2. Select **Control Panel > Add/Remove Programs > HP Software Agent for Microsoft Terminal Server** and click **Change/Remove**.

## How to Add Image Synchronization Points to a Script

**Note:** This topic applies to RDP Vuser scripts only.

1. Select an operation to which you would like to add a synchronization point in your script.
2. Right-click on the image snapshot and select **Insert Synch On Image** from the menu. The cursor will change to a cross-hair.
3. Mark the area on the screen that you would like to synchronize upon by clicking on the left button and dragging the box to enclose the area. When you release the mouse button, the **Sync on Image** dialog box opens.
4. Click **OK**. VuGen adds a new Sync on Image step before the selected step. When you select this step, VuGen displays a snapshot that contains a pink box around the area you selected for synchronization.

The next time you replay the script, it will wait until the image returned by the server matches the image you selected.

## Failed Image Synchronization Dialog Box (RDP Protocol)

This dialog box opens when an image synchronization fails during the replay of a script. You can stop the script or continue the replay despite the error.

<b>To access</b>	Opens automatically when an image synchronization fails.
<b>Important information</b>	<p><b>The content of this dialog box varies depending on the reason for the failed synchronization:</b></p> <ul style="list-style-type: none"> <li>• <b>Append Snapshot.</b> The Failed Image Synchronization - Append Snapshot dialog box opens when the replay image is so different from the record image that changing the tolerance level will not help.</li> <li>• <b>Raise Tolerance.</b> The Failed Image Synchronization - Raise Tolerance dialog box opens when the script replay failed to find the exact image requested, but if the tolerance level for performing synchronization on images was relaxed, then it would have succeeded in finding the image.</li> <li>• <b>Lower Tolerance.</b> The Failed Image Synchronization - Lower Tolerance dialog box opens when the script replay fails to meet the NotAppear or Change conditions. VuGen detected an image match where you expected it not to detect one. If the tolerance level was reduced, the recorded and replay images would not match, and the NotAppear or Change conditions would be met resulting in a successful replay.</li> <li>• <b>Non Specified.</b> The Failed Image Synchronization dialog box opens when the script replay fails to meet any of the synchronization conditions such as NotAppear or Change. VuGen did not find another image at the original coordinates that could be appended to the script.</li> </ul>
<b>See also</b>	<a href="#">Image Synchronization Overview</a>

User interface elements are described below:

UI Element	Description
<b>Stop</b>	Consider the mismatch between the snapshots to be an error. This error will be handled like all other errors and halt the execution of the script.

**, continued**

<b>Continue</b>	<p>This button performs different actions depending on the type of dialog box:</p> <ul style="list-style-type: none"> <li><b>Append Snapshot.</b> Accept the mismatch. VuGen appends the replay snapshot as a "record" snapshot for the step. In future replays of the step, VuGen uses all existing record snapshots and the appended snapshot as the basis for comparison between screens. If the replay returns any of the record snapshots, the Vuser will not fail. You can view the original and appended snapshots for a step by clicking the navigation arrows   in the Snapshot pane toolbar.</li> <li><b>Lower Tolerance.</b> Accept the mismatch and lower the tolerance level so that VuGen permits a smaller mismatch between the record images and those displayed during replay.</li> <li><b>Raise Tolerance.</b> Accept the mismatch and raise the tolerance level so that VuGen permits a greater mismatch between the record images and those displayed during replay.</li> <li><b>Non-specified.</b> Accept the mismatch, and do not make any changes in the script. Continue script execution despite the mismatch.</li> </ul> <p><b>Note:</b> Raising or lowering the tolerance level from the dialog box changes the level for the current step only. To change the tolerance level for the whole script, change the <b>Default tolerance for image synchronization</b> setting in the <b>Run-Time Settings &gt; RDP &gt; Synchronization</b> node.</p>
-----------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## RDP - Troubleshooting and Limitations

**Note:** This topic applies to RDP Vuser scripts only.

This section describes troubleshooting information for RDP scripts using the Agent for Microsoft Terminal Server.

### Replay fails on rdp\_sync\_object\_mouse\_click/double\_click steps

If the replay fails on specific `rdp_sync_object_mouse_click` or `rdp_sync_object_mouse_double_click` steps, there are workarounds to resolve the issue. We recommend that you try the workarounds in the order they are listed.

### Workaround: Modify RDPAgentCodeGen.cfg file

The `RDPAgentCodeGen.cfg` file can configure VuGen to automatically create an `rdp_sync_on_image` and `rdp_mouse_click` step the next time the script is generated for each `rdp_sync_object_mouse_click/double_click` steps which occur within a given window. To do this, you specify the name of the window, update a variable which counts the total number of windows for which this process occurs, and regenerate the script.

Modify the RDPAgentCodeGen.cfg file

1. Open the **RDPAGenCodeGen.cfg** file in the **Script Directory > data** folder.
2. Open the **Step Navigator** and double-click the step that failed.
3. Copy the name of the window
4. In the **RDPAGenCodeGen.cfg** file, increase the value of **NumberOfTitles** by 1.
5. Add a line as follows:

`WindowTitleX=<name of window>`

where **X** is the new value of **NumberOfTitles**.

6. Regenerate the script.

**Note:** The **RDPAGenCodeGen.cfg** file can be used to automatically produce **rdp\_sync\_on\_image** and **rdp\_mouse\_click** steps in a similar way for **rdp\_sync\_object\_mouse\_click/double\_click** steps which are specified in different ways as well. Steps can be targeted based on the class attribute of the control. For more information, contact HP software support.

### Workaround: Manually Insert a New Step

You can manually perform the workaround, by inserting an **rdp\_sync\_on\_image** and **rdp\_mouse\_click** step for each step that fails. We do not recommend using this workaround because steps added in this way will be lost if the script is regenerated.

- Clipboard sharing supports only short simple textual content.
- When recording with RDP Agent, applications which were developed using CBuilder may not record properly.
- RDP does not support 32-bit color depth. If recording uses this color depth, VuGen automatically switches to a lower color depth and a "[RDP Analyzer Warning (790: 418)] 32-bit color depth is not supported, switch to lower one". warning log item appears in the Recording Window.

## RTE Protocol

### RTE Protocol Overview

An RTE Vuser types character input into a terminal emulator, submits the data to a server, and then waits for the server to respond. For instance, suppose that you have a server that maintains customer information for a maintenance company. Each time a field service representative makes a repair, he accesses the server database by modem using a terminal emulator. The service representative accesses information about the customer and then records the details of the repair that he performs.

You could use RTE Vusers to emulate this case. An RTE Vuser would:

1. Type **60** at the command line to open an application program.
2. Type **F296**, the field service representative's number.
3. Type **NY270**, the customer number.
4. Wait for the word "Details" to appear on the screen. The appearance of "Details" indicates that all the customer details are displayed on the screen.
5. Type **Changed gasket P249, and performed Major Service** the details of the current repair.
6. Type **Q** to close the application program.

You use VuGen to create RTE Vuser scripts. The script generator records the actions of a human user on a terminal emulator. The script generator records the keyboard input from the terminal window, generates the appropriate statements, and inserts them into the Vuser script. While you record, the script generator automatically inserts synchronization functions into the script. For details, see "[RTE Synchronization Overview](#)" on page 766.

The functions developed to emulate a terminal communicating with a server are called TE Vuser functions. Each TE Vuser function has a **TE** prefix. VuGen automatically records most of the TE functions listed in this section during an RTE recording session. You can also manually program any of the functions into your script.

For syntax and examples of the TE functions, see the Function Reference ([Help > Function Reference](#)).

An RTE Vuser emulates the actions of a real user. Human users use terminals or terminal emulators to operate application programs.



In the RTE Vuser environment, a Vuser replaces the human. The Vuser operates PowerTerm, a terminal emulator.



PowerTerm works like a standard terminal emulator, supporting common protocols such as IBM 3270 =; 5250, VT100, VT220, and VT420-7.

## Working with Ericom Terminal Emulation

VuGen supports record and replay with Ericom Terminal Emulators.


The Ericom support handles escape sequences during record and replay. Ericom's PowerTerm lets you map PC keys to custom escape sequences. For information about mapping, see the PowerTerm help.

When a user presses mapped keys while recording an Ericom VT session, VuGen generates **TE\_send\_text** functions instead of the standard **TE\_type**. This allows the script to handle custom escape sequences in a single step. For more information, see the Function Reference (**Help > Function Reference**) for the **TE\_send\_text** function.

## SSL and SSH Support for Ericom

VuGen also supports SSL/SSH record and replay for the RTE Ericom library. To work with SSL or SSH, you select the type in the **Security** section of the Connect dialog box.

When working with SSH Security, by default VuGen opens a popup dialog box prompting you for more information. We recommend that you disable the **Show** options to prevent the pop-ups from being issued. If you enable these pop-ups, it may affect the replay. You can access the advanced security options by clicking the **Details** button.



## Typing Input into a Terminal Emulator

Two TE Vuser functions enable Vusers to "type" character input into the PowerTerm terminal emulator:

- **TE\_type** sends characters to the terminal emulator. When recording, the VuGen automatically generates **TE\_type** functions for keyboard input to the terminal window. For details, see below.
- **TE\_typing\_style** determines the speed at which the Vuser types. You can manually define the typing style by inserting a **TE\_typing\_style** function into the Vuser script. Alternatively, you can set the typing style by using the run-time settings. For more information, see "["Run-Time Settings" on page 317](#).

**Note:** While recording an RTE Vuser script, do not use the mouse to relocate the cursor within the terminal emulator window. VuGen does not record these cursor movements.

### Using the **TE\_type** Function

When you record a script, the VuGen records all keyboard input and generates appropriate **TE\_type** functions. During execution, **TE\_type** functions send formatted strings to the terminal emulator.

Keyboard input is defined as a regular text string (including blank spaces). For example:

```
TE_type ("hello, world");
```

Input key names longer than one character are represented by identifiers beginning with the letter k, and are bracketed within greater-than/less-than signs (< >).

For example, the following function depicts the input of the Return key followed by the Control and y keys:

```
TE_type("<kReturn><kControl-y>");
```

Some other examples include: <kF1>, <kUp>, <kF10>, <kHelp>, <kTab>.

To determine a key name, record an operation on the key, and then check the recorded statement for its name.

**Note:** When you program a **TE\_type** statement (rather than recording it), use the key definitions provided in the Function Reference ([Help > Function Reference](#)).

### Setting the Timeout Value for **TE\_type**

If a Vuser attempts to submit a **TE\_type** statement while the system is in X SYSTEM (or input inhibited) mode, the Vuser will wait until the X SYSTEM mode ends before typing. If the system stays in X SYSTEM mode for more than **TE\_XSYSTEM\_TIMEOUT** milliseconds, then the **TE\_type** function returns a **TE\_TIMEOUT** error.

You can set the value of **TE\_XSYSTEM\_TIMEOUT** by using **TE\_setvar**. The default value for **TE\_XSYSTEM\_TIMEOUT** is 30 seconds.

## Allowing a Vuser to Type Ahead

Under certain circumstances you may want a Vuser to submit a keystroke even though the system is in X SYSTEM (or input inhibited) mode. For example, you may want the Vuser to press the Break key. You use the TE\_ALLOW\_TYPEAHEAD variable to enable the Vuser to submit a keystroke even though the system is in X SYSTEM mode.

Set TE\_ALLOW\_TYPEAHEAD to zero to disable typing ahead, and to any non-zero number to permit typing ahead. You use **TE\_setvar** to set the value of TE\_ALLOW\_TYPEAHEAD. By default, TE\_ALLOW\_TYPEAHEAD is set to zero, preventing keystrokes from being sent during X SYSTEM mode.

For more information about the **TE\_type** function and its conventions, see the Function Reference ([Help > Function Reference](#)).

### Setting the Typing Style

You can set two typing styles for RTE Vuser: FAST and HUMAN. In the FAST style, the Vuser types input into the terminal emulator as quickly as possible. In the HUMAN style, the Vuser pauses after typing each character. In this way, the Vuser more closely emulates a human user typing at the keyboard.

You set the typing style using the **TE\_typing\_style** function. The syntax of the **TE\_typing\_style** function is:

```
int TE_typing_style (char * style);
```

where style can be FAST or HUMAN. The default typing style is HUMAN. If you select the HUMAN typing style, the format is:

HUMAN, delay [, first\_delay]

The delay indicates the interval (in milliseconds) between keystrokes. The optional parameter first\_delay indicates the wait (in milliseconds) before typing the first character in the string. For example,

```
TE_typing_style ("HUMAN, 100, 500");
TE_type ("ABC");
```

means that the Vuser will wait 0.5 seconds before typing the letter A; it will then wait 0.1 seconds before typing "B" and then a further 0.1 seconds before typing "C".

For more information about the **TE\_typing\_style** function and its conventions, see the Function Reference ([Help > Function Reference](#)).

In addition to setting the typing style by using the **TE\_typing\_style** function, you can also use the run-time settings. For details, see "[Run-Time Settings](#)" on page 317.

## Generating Unique Device Names

Some protocols, such as APPC, require a unique device name for each terminal that logs on to the system. Using the run-time settings, you can specify that the **TE\_connect** function generate a unique 8-character device name for each Vuser, and connect using this name. Although this solves

the requirement for uniqueness, some systems have an additional requirement: The device names must conform to a specific format. See ["Run-Time Settings" on page 317](#) for more information.

To define the format of the device names that the **TE\_connect** function uses to connect a Vuser to the system, add an **RteGenerateDeviceName** function to the Vuser script. The function has the following prototype:

```
void RteGenerateDeviceName(char buf[32])
```

The device name should be written into **buf**.


If an **RteGenerateDeviceName** function exists in a Vuser script, the Vuser calls the function each time a new device name is needed. If no **RteGenerateDeviceName** function is defined in the script—and unique device names are required—the **TE\_connect** function generates the required names.

In the following example, the **RteGenerateDeviceName** function generates unique device names with the format "TERMx". The first name is TERM0, followed by TERM1, TERM2, and so forth.

```
RteGenerateDeviceName(char buf[32])
{
    static int n=0;
    sprintf(buf, "TERM%d", n);
    n=n+1;
}
```

## Setting the Field Demarcation Characters

Some terminal emulators use demarcation characters to mark the beginning and the end of each field. These demarcation characters are not visible—appearing on the screen as spaces. In the terminal emulator shown below, the colors in the middle section of the screen have been inverted to display the field demarcation characters. These characters are surrounded by ellipses.



The **TE\_wait\_text**, **TE\_get\_text**, and **TE\_find\_text** functions operate by identifying the characters in a specified portion of the screen. If a field demarcation character is located within the specified section, you can identify the character as a space or an ASCII character. You use the **TE\_FIELD\_CHARS** system variable to specify the method of identification. You can set **TE\_FIELD\_CHARS** to 0 or 1:

- 0 specifies that the character in the position of the field demarcation characters is returned as a space.
- 1 specifies that the character in the position of the field demarcation characters is returned as an ascii code (ascii 0 or ascii 1).

By default, **TE\_FIELD\_CHARS** is set to 0.

You retrieve and set the value of **TE\_FIELD\_CHARS** by using the **TE\_getvar** and **TE\_setvar** functions.

## Reading Text from the Terminal Screen

There are several Vuser functions that RTE Vusers can use to read text from the terminal screen. You can use these functions, **TE\_find\_text** and **TE\_get\_text\_line**, to check that the terminal emulator is responding correctly, or to enhance the logic in your scripts.

After recording, you can manually insert **TE\_find\_text** and **TE\_get\_text\_line** statements directly into your RTE Vuser scripts.

## Searching for Text on the Screen

The **TE\_find\_text** function searches for a line of text on the screen. The syntax of the function is:

```
int TE_find_text (char *pattern, int col1, int row1, int col2, int row2,
                  int *retcol, int *retrow, char *match );
```

This function searches for text matching pattern within the rectangle defined by col1, row1, col2, row2. Text matching the pattern is returned to match, and the actual row and column position is returned to retcol and retrow. The search begins in the top-left corner. If more than one string matches pattern, the one closest to the top-left corner is returned.

The **pattern** can include a regular expression. See the Function Reference ([Help > Function Reference](#)) for details on using regular expressions.

You must manually type **TE\_find\_text** statements into your Vuser scripts. For details on the syntax of the **TE\_find\_text** function, see the Function Reference ([Help > Function Reference](#)).

## Reading Text from the Screen

The **TE\_get\_text\_line** function reads a line of text from the area of the screen that you designate. The syntax of the function is:

```
char *TE_get_text_line (int col, int row, int width, char * text );
```

This function copies a line of text from the terminal screen to a buffer text. The first character in the line is defined by col, row. The column coordinate of the last character in the line is indicated by width. The text from the screen is returned to the buffer text. If the line contains tabs or spaces, the equivalent number of spaces is returned.

In addition, the **TE\_get\_cursor\_position** function can be used to retrieve the current position of the cursor on the terminal screen. The **TE\_get\_line\_attribute** function returns the character formatting (for instance, bold or underline) of a line of text.

You must manually type **TE\_get\_text\_line** statements into your Vuser scripts. For details on the syntax of the **TE\_get\_text\_line** function, see the Function Reference ([Help > Function Reference](#)).

## RTE Synchronization Overview

Depending on the system you are testing, you may need to synchronize the input that a Vuser sends to a terminal emulator with the subsequent responses from the server. When you synchronize input, you instruct the Vuser to suspend script execution and wait for a cue from the system, before the Vuser performs its next action. For instance, suppose that a human user wants to submit the following sequence of key strokes to a bank application:

1. Type 1 to select "Financial Information" from the menu of a bank application.
2. When the message "What information do you require?" appears, type 3 to select "Dow Jones

"Industrial Average" from the menu.

3. When the full report has been written to the screen, type 5 to exit the bank application.

In this example, the input to the bank application is synchronized because at each step, the human user waits for a visual cue before typing.

This cue can be either the appearance of a particular message on the screen, or stability of all the information on the screen.

You can synchronize the input of a Vuser in the same way by using the TE-synchronization functions, **TE\_wait\_sync**, **TE\_wait\_text**, **TE\_wait\_silent**, and **TE\_wait\_cursor**. These functions effectively emulate a human user who types into a terminal window and then waits for the server to respond, before typing in the next command.

The **TE\_wait\_sync** function is used to synchronize block-mode (IBM) terminals only. The other TE-synchronization functions are used to synchronize character-mode (VT) terminals.

When you record an RTE Vuser script, VuGen can automatically generate and insert **TE\_wait\_sync**, **TE\_wait\_text**, and **TE\_wait\_cursor** statements into the script. You use VuGen's recording options to specify which synchronization functions VuGen should insert.

**Note:** Do not include any synchronization statements in the Vuser\_end section of a Vuser script. Since a Vuser can be aborted at any time, you cannot predict when the Vuser\_end section will be executed.

## Synchronizing Block-Mode (IBM) Terminals

The **TE\_wait\_sync** function is used for synchronization RTE Vusers operating block-mode (IBM) terminals. Block-mode terminals display the "X SYSTEM" message to indicate that the system is in Input Inhibited mode. When a system is in the Input Inhibited mode no typing can take place because the terminal emulator is waiting for a transfer of data from the server.

When you record a script on a block-mode terminal, by default, VuGen generates and inserts a **TE\_wait\_sync** function into the script each time the "X SYSTEM" message appears. You use VuGen's recording options to specify whether or not VuGen should automatically insert **TE\_wait\_sync** functions.

When you run a Vuser script, the **TE\_wait\_sync** function checks if the system is in the X SYSTEM mode. If the system is in the X SYSTEM mode, the **TE\_wait\_sync** function suspends script execution. When the "X SYSTEM" message is removed from the screen, script execution continues.

**Note:** You can use the **TE\_wait\_sync** function only with IBM block-mode terminals emulators (5250 and 3270).

In general, the **TE\_wait\_sync** function provides adequate synchronization for all block-mode terminal emulators. However, if the **TE\_wait\_sync** function is ineffective in a particular situation, you can enhance the synchronization by including a **TE\_wait\_text** function. For more information on

the **TE\_wait\_text** function, see "[Synchronizing Character-Mode \(VT\) Terminals](#)" on the next page, and the Function Reference ([Help > Function Reference](#)).

In the following script segment, the Vuser logs on with the user name "QUSER" and the password "HPLAB". The Vuser then presses Enter to submit the login details to the server. The terminal emulator displays the X SYSTEM message while the system waits for the server to respond.

The **TE\_wait\_sync** statement causes the Vuser to wait until the server has responded to the login request, that is, for the X SYSTEM message to be removed—before executing the next line of the script.

```
TE_type("QUSER");
lr_think_time(2);
TE_type("<kTab>HPLAB");
lr_think_time(3);
TE_type("<kEnter>");
TE_wait_sync();
....
```

When a **TE\_wait\_sync** function suspends the execution of a script while an X SYSTEM message is displayed, the Vuser continues to monitor the system—waiting for the X SYSTEM message to disappear. If the X SYSTEM message does not disappear before the synchronization timeout expires, the **TE\_wait\_sync** function returns an error code. The default timeout is 60 seconds.

## **Set the TE\_wait\_sync synchronization timeout**

1. Select **Vuser > Run-Time Settings**. The Run-Time Settings dialog box appears.
2. Select the **RTE:RTE** node in the Run-Time setting tree.
3. Under **X SYSTEM Synchronization**, enter a value (in seconds) in the **Timeout** box.
4. Click **OK** to close the Run-Time Settings dialog box.

After a Vuser executes a **TE\_wait\_sync** function, the Vuser waits until the terminal is no longer in the X SYSTEM mode. When the terminal returns from the X SYSTEM mode, the Vuser continues to monitor the system for a short period to verify that the terminal is fully stable, that is, that the system does not return to the X SYSTEM mode. Only then does the **TE\_wait\_sync** function terminate and allow the Vuser to continue executing its script. The period that the Vuser continues to monitor the system, after the system has returned from the X SYSTEM mode, is known as the stable time. The default stable time is 1000 milliseconds.

You may need to increase the stable time if your system exhibits the following behavior:

When a system returns from the X SYSTEM mode, some systems "flickers" to and from the X SYSTEM for a short period of time until the system stabilizes. If the system remains out of the X SYSTEM mode for more than one second, and then returns to the X SYSTEM mode, the **TE\_wait\_sync** function will assume that the system is stable. If a Vuser then tries to type information to the system, the system will shift into keyboard-locked mode.

Alternatively, if your system never flickers when it returns from the X SYSTEM mode, you can reduce the stable time to less than the default value of one second.

## Change the stable time for TE\_wait\_sync functions

1. Select **Vuser > Run-Time Settings**. The Run-Time Settings dialog box appears.
2. Select the **RTE:RTE** node.
3. Under **X SYSTEM Synchronization**, enter a value (in milliseconds) in the **Stable time** box.
4. Click **OK** to close the Run-Time Settings dialog box.

For more information on the **TE\_wait\_sync** function, see the Function Reference (**Help > Function Reference**).

You can instruct VuGen to record the time that the system remains in the X SYSTEM mode each time that the X SYSTEM mode is entered. To do so, VuGen inserts a **TE\_wait\_sync\_transaction** function after each **TE\_wait\_sync** function, as shown in the following script segment:

```
TE_wait_sync();
TE_wait_sync_transaction("syncTrans1");
```

Each **TE\_wait\_sync\_transaction** function creates a transaction with the name "default." This allows you to analyze how long the terminal emulator waits for responses from the server during a scenario run. You use the recording options to specify whether VuGen should generate and insert **TE\_wait\_sync\_transaction** statements.

Instruct VuGen to insert **TE\_wait\_sync\_transaction** statements

1. Select **Vuser > Recording Options**. The Recording Settings dialog box appears.
2. Select the **Generate Automatic X SYSTEM transactions** option, and then click **OK**.

## Synchronizing Character-Mode (VT) Terminals

There are three types of synchronization that you can use for character-mode (VT) terminals. The type of synchronization that you select depends on:

- the design of the application that is running in the terminal emulator
- the specific action to be synchronized

### Waiting for the Cursor to Appear at a Specific Location

The preferred method of synchronization for VT type terminals is cursor synchronization. Cursor synchronization is particularly useful with full-screen or form-type applications, as opposed to scrolling or TTY-type applications.

Cursor synchronization uses the **TE\_wait\_cursor** function. When you run an RTE Vuser script, the **TE\_wait\_cursor** function instructs a Vuser to suspend script execution until the cursor appears at a specified location on the screen. The appearance of the cursor at the specified location means that the application is ready to accept the next input from the terminal emulator.

The syntax of the **TE\_wait\_cursor** function is:

```
int TE_wait_cursor (int col, int row, int stable, int timeout );
```

During script execution, the **TE\_wait\_cursor** function waits for the cursor to reach the location specified by col , row.

The **stable** parameter specifies the time (in milliseconds) that the cursor must remain at the specified location. If you record a script using VuGen, **stable** is set to 100 milliseconds by default. If the client application does not become stable in the time specified by the **timeout** parameter, the function returns TIMEOUT. If you record a script using VuGen, **timeout** is set by default to the value of TIMEOUT, which is 90 seconds. You can change the value of both the **stable** and **timeout** parameters by directly editing the recorded script.

The following statement waits for the cursor to remain stable for three seconds. If the cursor doesn't stabilize within 10 seconds, the function returns TIMEOUT.

```
TE_wait_cursor (10, 24, 3000, 10);
```

For more information on the **TE\_wait\_cursor** function, see the Function Reference ([Help > Function Reference](#)).

You can instruct VuGen to automatically generate **TE\_wait\_cursor** statements, and insert them into a script, while you record the script. The following is an example of a **TE\_wait\_cursor** statement that was automatically generated by VuGen:

```
TE_wait_cursor(7, 20, 100, 90);
```

### Instruct VuGen to automatically generate **TE\_wait\_cursor** statements, and insert them into a script while recording

1. Select **Vuser > Recording Options**. The Recording Settings dialog box appears.
2. Under **Generate Automatic Synchronization Commands** select the **Cursor** check box, and then click **OK**.

#### Waiting for Text to Appear on the Screen

You can use text synchronization to synchronize an RTE Vuser running on a VT terminal emulator. Text synchronization uses the **TE\_wait\_text** function. During script execution, the **TE\_wait\_text** function suspends script execution and waits for a specific string to appear in the terminal window before continuing with script execution. Text synchronization is useful with those applications in which the cursor does not consistently appear in a predefined area on the screen.

**Note:** Although text synchronization is designed to be used with character mode (VT) terminals, it can also be used with IBM block-mode terminals. Do not use automatic text synchronization with block-mode terminals.

The syntax of the **TE\_wait\_text** function is:

```
int TE_wait_text (char * pattern, int timeout, int col1, int row1, int col2, int row2,
                 int * retcol, int * retrow, char * match );
```

This function waits for text matching pattern to appear within the rectangle defined by col1, row1, col2, row2. Text matching the pattern is returned to **match**, and the actual row and column position

is returned to **retcol** and **retrow**. If the **pattern** does not appear before the **timeout** expires, the function returns an error code. The **pattern** can include a regular expression. See the Function Reference for details on using regular expressions. Besides the **pattern** and **timeout** parameters, all the other parameters are optional.

If **pattern** is passed as an empty string, the function will wait for timeout if it finds any text at all within the rectangle. If there is no text, it returns immediately.

If the pattern does appear, then the function waits for the emulator to be stable (finish redrawing, and not display any new characters) for the interval defined by the **TE\_SILENT\_SEC** and **TE\_SILENT\_MILLI** system variables. This, in effect, allows the terminal to become stable and emulates a human user.

If the terminal does not become stable within the interval defined by **TE\_SILENT\_TIMEOUT**, script execution continues. The function returns 0 for success, but sets the **TE\_errno** variable to indicate that the terminal was not silent after the text appeared.

To modify or retrieve the value of any of the **TE\_SILENT** system variables, use the **TE\_getvar** and **TE\_setvar** functions. For more information, see the Function Reference (**Help > Function Reference**).

In the following example, the Vuser types in its name, and then waits for the application to respond.

```
/* Declare variables for TE_wait_text */
int ret_row;
int ret_col;
char ret_text [80];
/* Type in user name. */
TE_type ("John");
/* Wait for teller to respond. */
TE_wait_text ("Enter secret code:", 30, 29, 13, 1, 13, =;ret_col, =;ret_row,
              ret_text);
```

You can instruct VuGen to automatically generate **TE\_wait\_text** statements, and insert them into a script, while you record the script.

### **Instruct VuGen to automatically generate TE\_wait\_text statements, and insert them into a script while recording**

1. Select **Vuser > Recording Options**. The Recording Settings dialog box appears.
2. Under **Generate Automatic Synchronization Commands**, select the **Prompt** check box, and then click **OK**.

The following is an example of a **TE\_wait\_text** statement that was automatically generated by VuGen. The function waits up to 20 seconds for the string "keys" to appear anywhere on the screen. Note that VuGen omits all the optional parameters when it generates a **TE\_wait\_text** function.

```
TE_wait_text("keys", 20);
```

## Waiting for the Terminal to be Silent

In instances when neither cursor synchronization nor text synchronization are effective, you can use "silent synchronization" to synchronize the script. With "silent synchronization," the Vuser waits for the terminal emulator to be silent for a specified period of time. The emulator is considered to be silent when it does not receive any input from the server for a specified period of time.

**Note:** Use silent synchronization only when neither cursor synchronization nor text synchronization are effective.

You use the **TE\_wait\_silent** function to instruct a script to wait for the terminal to be silent. You specify the period for which the terminal must be silent. If the terminal is silent for the specified period, then the **TE\_wait\_silent** function assumes that the application has stopped printing text to the terminal screen, and that the screen has stabilized.

The syntax of the function is:

```
int TE_wait_silent (int sec, int milli, int timeout );
```

The **TE\_wait\_silent** function waits for the terminal emulator to be silent for the time specified by sec (seconds) and milli (milliseconds). The emulator is considered silent when it does not receive any input from the server. If the emulator does not become silent (i.e. stop receiving characters) during the time specified by the time timeout variable, then the function returns an error.

For example, the following statement waits for the screen to be stable for three seconds. If after ten seconds, the screen has not become stable, the function returns an error.

```
TE_wait_silent (3, 0, 10);
```


For more information, see the Function Reference ([Help > Function Reference](#)).

## How to Map Terminal Keys to PC Keyboard Keys

Because you are using a terminal emulator, you will be using a PC keyboard in place of a terminal keyboard. Many keys that are found on the terminal keyboard are not available on a PC keyboard. Examples of such keys are HELP, AUTHOR, and PUSH, which are found on the IBM 5250 keyboard. To successfully operate the terminal emulator and any associated application programs, you may have to map certain terminal keys to keys on the PC keyboard.

### Map a Terminal Key to a Key on the PC Keyboard

1. In the terminal emulator, select **Options > Keyboard Map**, or click the **Keyboard Mapping** button . The Keyboard Mapping dialog box opens.



2. Click the **Keyboard Mapping** button on the toolbar. To map a terminal key to a PC key, drag a key from the upper terminal keyboard to a PC key on the lower keyboard.

You can click the Shift and/or Control keys on the upper keyboard to display additional key functions that can be viewed only by first selecting either of these keys. You can then drag the required key from the upper terminal keyboard to a key on the lower PC keyboard.

To cancel a definition, drag the PC key definition to the wastebasket. This restores the default function of the PC key.

To restore the default mappings, click **Defaults**.

## How to Record RTE Vuser Scripts

You use VuGen to record RTE Vuser scripts. VuGen uses the PowerTerm terminal emulator to emulate a wide variety of terminal types.

This task describes how to record RTE Vuser scripts. This procedure differs from the general recording procedure in "[Recording a Vuser Script](#)" on page 174.

1. **Record the terminal setup and connection**

- Open an existing RTE Vuser script, or create a new one.
- In the **Sections** box, select the **vuser\_init** section to insert the recorded statements.

- c. In the Vuser script, place the cursor at the location where you want to begin recording.
- d. Click the **Start Record** button  **Start Record**. The PowerTerm main window opens.
- e. From the PowerTerm menu bar, select **Terminal > Setup** to display the Terminal Setup dialog box.
- f. Select the type of emulation from the VT Terminal and IBM Terminal types, and then click **OK**.

**Note:** Select an IBM terminal type to connect to an AS/400 machine or an IBM mainframe; select a VT terminal type to connect to a Linux workstation.

- g. Select **Communication > Connect** to display the Connect dialog box.
- h. Under **Session Type**, select the type of communication to use.
- i. Under **Parameters**, specify the required options. The available parameters vary depending on the type of session that you select. For details on the parameters, click **Help**.

**Tip:** Click **Save As** to save the parameter-sets for re-use in the future. The parameter-sets that you save are displayed in the Sessions List box.

- j. Click **Connect**. PowerTerm connects to the specified system, and VuGen inserts a **TE\_connect** function into the script, at the insertion point. The **TE\_connect** statement has the following form:

```
/* *** The terminal type is VT 100. */
TE_connect(
    "comm-type = telnet;"  

    "host-name = alfa;"  

    "telnet-port = 992;"  

    "terminal-id = ;"  

    "set-window-size = true;"  

    "security-type = ssl;"  

    "ssl-type = tls1;"  

    "terminal-type = vt100;"  

    "terminal-model = vt100;"  

    "login-command-file = ;"  

    "terminal-setup-file = ;"  

    , 60000);
if (TE_errno != TE_SUCCESS)
    return -1;
```

The inserted **TE\_connect** statement is followed by an if statement that checks whether or not the **TE\_connect** function succeeds during replay.

**Note:** Do not record more than one connection to a server (**TE\_connect**) in a Vuser script.

## 2. Record typical user actions

After recording the setup procedure, you perform typical user actions or business processes. You record these processes into the **Actions** section of the Vuser script. Only the **Actions** section of a Vuser script is repeated when you run multiple iterations of the script.

When recording a session, VuGen records the text strokes and not the text. Therefore, it is not recommended that you copy and paste commands into the PowerTerm window—instead, type them in directly.

- a. Select the **Actions** section in the **Section** box.
- b. Proceed to perform typical user actions in the terminal emulator. VuGen generates the appropriate statements, and inserts them into the Vuser script while you type. If necessary, you can edit the recorded statements while you record the script.

## 3. Record the log-off procedure

- a. Make sure that you have performed and recorded the typical user actions as described in the previous section.
- b. In the VuGen main window, click **vuser\_end** in the **Section** box.
- c. Perform the log off procedure. VuGen records the procedure into the **vuser\_end** section of the script.
- d. Click **Stop Recording**  on the Recording toolbar. The main VuGen window displays all the recorded statements.
- e. Click  **Save** to save the recorded session. After recording a script, you can manually edit it in VuGen's main window.

# How to Implement Continue on Error

To configure the Continue on Error functionality in RTE Scripts:

- To continue running the script on error, insert the following function:

**TE\_setvar(TE\_IGNORE\_ERRORS, 1)**

- To restore the default behavior of failing the script on error, insert the following function:

**TE\_setvar(TE\_IGNORE\_ERRORS, 0)**

# RTE - Terminal Emulation - Troubleshooting and Limitations

This section describes troubleshooting and limitations for RTE Vusers.

- IP spoofing is not supported for RTE Vusers.
- The running of RTE scripts from the Controller is not supported on Windows 8 or Server 2012.

## SAP Protocols

### Selecting a SAP Protocol Type

- To test the SAP GUI user operating only on the client, use the SAP GUI Vuser type.
- To test a SAP GUI user that also uses a Web browser, use the SAP (Click & Script) or SAP-Web protocol.

To record a SAP GUI session that uses browser controls, create a multi-protocol Vuser script with the SAP GUI and SAP-Web protocols. This allows VuGen to record Web-specific functions when encountering the browser controls. This will not work if you attempt to combine SAP GUI and Web protocols.


Before recording a session, verify that your modules and client interfaces are supported by VuGen. The following table describes the SAP client modules for SAP Business applications and the relevant tools:

SAP module	VuGen support
SAP Web Client or mySAP.com	Use the SAP-Web protocol.
SAP GUI for Windows	Use the SAP GUI protocol. This also supports APO module recording (requires patch level 24 for APO 3.0 for SAP 6.20).
SAP GUI for Windows and a web browser	Use the SAP (Click & Script) protocol.
SAP GUI for Java	This client is not supported.


## SAP GUI Protocol

The SAP GUI Vuser script typically contains several SAP transactions which make up a business process. A business process consists of functions that emulate user actions. Open the **Step Navigator** to see each user action as a Vuser script step.


The following example shows a typical recording of a SAP GUI client. The first section, **vuser\_init**, contains the opening of a connection and a logon.



Note that the Open Connection step uses one of the connection names in the SAP Logon **Descriptions** list. If the specified connection name is not in the list, the Vuser looks for a server with that name.



In the following section, the functions emulate typical user operations such as menu selection and the setting of a check box.



The final section, **vuser\_end**, illustrates the logoff procedure.



When recording a multi- protocol script for both SAP GUI and Web, VuGen generates steps for both protocols. In the Script view, you can view both **sapgui** and **web** functions.

The following example illustrates a multi-protocol recording in which the SAP GUI client opens a Web control. Note the switch from **sapgui** to **web** functions.

```
sapgui_tree_double_click_item("Use as general WWW browser, REPTITLE",
    "shellcont/shell",
    "000732",
    "REPTITLE",
    BEGIN_OPTIONAL,
    "AdditionalInfo=sapgui1020",
    END_OPTIONAL);
```

```

...
sapgui_set_text("", 
    "http:\\\\yahoo.com",
    "usr/txtEDURL",
    BEGIN_OPTIONAL,
    "AdditionalInfo=sapgui1021",
    END_OPTIONAL);
...
web_add_cookie("B=7pt5c1sv1p3m2=;b=2; DOMAIN=www.yahoo.com");
web_url("yahoo.com",
    "URL=http://yahoo.com/",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t1.inf",
    "Mode=HTML",
    EXTRARES,
    "URL=http://srd.yahoo.com/hpt1/ni=17/ct=lan/sss=1043752588/t1=1043752575385/d1=1
251
    /d2=1312/d3=1642/d4=4757/0.4097009487287739/*1",
    "Referer=http://www.yahoo.com/", ENDITEM,
    LAST);

```

## SAP Web Protocol

The SAP-Web Vuser script typically contains several SAP transactions which make up a business process. The business process consists of functions that emulate user actions. For information about these functions, see the Web functions in the Function Reference (**Help > Function Reference**).

### Example:

The following example shows a typical recording for an SAP Portal client:

```

vuser_init()
{
    web_reg_find("Text=SAP Portals Enterprise Portal 5.0",
        LAST);
    web_set_user("junior{UserNumber}",
        lr_decrypt("3ed4cf457afe04e"),
        "sonata.hplab.com:80");
    web_url("sapportal",
        "URL=http://sonata.hplab.com/sapportal",
        "Resource=0",
        "RecContentType=text/html",
        "Snapshot=t1.inf",
        "Mode=HTML",
        EXTRARES,
        "Url=/SAPPortal/IE/Media/sap_mango_polarwind/images/header/branding_imag
e.jpg",

```

```

    "Referer=http://sonata.hplab.com/hrnp$30001/sonata.hplab.com:80/Action/26011[header]"
        , ENDITEM,
    "Url=/SAPPortal/IE/Media/sap_mango_polarwind/images/header/logo.gif",
    "Referer=http://sonata.hplab.com/hrnp$30001/sonata.hplab.com:80/Action/26011[header]",
        ENDITEM,
    ...
LAST);

```

The following section illustrates an SAP Web and SAP GUI multi-protocol recording in which the Portal client opens an SAP control. Note the switch from **web\_xxx** to **sapgui\_xxx** functions.

```

web_url("dummy",
    "URL=http://sonata.hplab.com:1000/hrnp$30000/sonata.hplab.com:
    1000/Action/dummy?PASS_PARAMS=YES=;dummyComp=dummy=;
Tcode=VA01=;draggable=0=;CompFName=VA01=;Style=sap_mango_polarwind",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=http://sonata.hplab.com/sapportal",
    "Snapshot=t9.inf",
    "Mode=HTML",
    LAST);
sapgui_open_connection_ex(" /H/Protector/S/3200 /WP",
    "",
    "con[0]");
sapgui_select_active_connection("con[0]");
sapgui_select_active_session("ses[0]");
/*Before running script, enter password in place of asterisks in logon function*/
sapgui_logon("JUNIOR{UserNumber}",
    "ides",
    "800",
    "EN",
    BEGIN_OPTIONAL,
    "AdditionalInfo=sapgui102",
    END_OPTIONAL);

```

## SAP (Click & Script) Protocol

VuGen can create Vuser scripts for SAP Enterprise portal7 and SAP ITS 6.20/6.40 environments using specialized test objects and methods that have been customized for SAP. The objects are APIs based on HP QuickTest or Unified Functional Testing support for SAP.

As you record a test or component on your SAP application, VuGen records the operations you perform. VuGen recognizes special SAP Windows objects such as frames, table controls, iViews, and portals.

For an overview on the Click and Script protocols, see ["Click & Script Protocols - Overview" on page 602](#).

VuGen supports recording for the following SAP controls: button, check box, drop-down menu, edit field, iview, list, menu, navigation bar, OK code, portal, radio group, status bar, tab strip, table, and tree view.

VuGen uses the control handler layer to create the effect of an operation on a GUI control. During recording, when encountering one of the supported SAP objects, VuGen generates a function with an **sap\_xxx** prefix.

**Example:**

In the following example, a user selected the **User Profile** tab. VuGen generated a **sap\_portal** function.

```
web_browser("Close_2",
    "Snapshot=t7.inf",
    DESCRIPTION,
    "Ordinal=2",
    ACTION,
    "UserAction=Close",
    LAST);
lr_think_time(7);
web_text_link("Personalize",
    "Snapshot=t8.inf",
    DESCRIPTION,
    "Text=Personalize",
    ACTION,
    "UserAction=Click",
    LAST);
lr_think_time(6);
sap_portal("Sap Portal_2",
    "Snapshot=t9.inf",
    DESCRIPTION,
    "BrowserOrdinal=2",
    ACTION,
    "DetailedNavigation=User Profile",
    LAST);
```

**Note:** When you record an SAP (Click & Script) session, VuGen generates standard Click & Script functions for objects that are not SAP-specific. You do not need to explicitly specify the Web protocol. In the example above, VuGen generated a **web\_text\_link** function when the user clicked the **Personalize** button.

## Replaying SAP GUI Optional Windows

When working with SAP GUI Vuser Scripts, you may encounter optional windows in the SAP GUI client—windows that were present during recording, but do not exist during replay. If you try to replay your recorded script as is, it will fail when it attempts to find the missing windows.

VuGen's optional window mechanism performs the actions on a window only after verifying that it exists. The Vuser checks if the window indicated in the **Select active window** step exists. If the

window is found during replay, it performs the actions as they were recorded in the script. If it does not exist, the Vuser ignores all window actions until the next **Select active window** step. Note that only SAP GUI steps (beginning with a **sapgui** prefix) are ignored.

To use this feature, in Tree view select the appropriate Select Active Window step and select **Run steps for window only if it exists** from the right-click menu.

To disable this feature and attempt to run these steps at all times, regardless of whether the Vuser finds the window or not, select **Always run steps for this window** from the right-click menu.

## How to Configure the SAP Environment

This task describes configure and verify the SAP environment for use with VuGen.

VuGen support for the SAP GUI for Windows client, is based on SAP's Scripting API. This API allows Vusers to interact with the SAP GUI client, receive notifications, and perform operations.

The Scripting API is available only in recent versions of the SAP Kernel. In kernel versions that support scripting, the option is disabled by default. In order to use VuGen, first make sure that the SAP servers support the Scripting API, and enable the API on both the server and clients. For more information and to download patches, see the SAP OSS note #480149.

### Checking the SAPGUI Scripting API is enabled.

Run the **VerifyScripting.exe** file from the **Additional Components\SAP\_Tools\VerifySAPGUI** folder. For details, see "[Additional Components](#)" on page 1741. For more information, see the file **VerifyScripting.htm** provided with this utility.

### Checking the SAP GUI for Windows Client Patch Level

You can check the patch level of your SAP GUI for Windows client from the About box. The lowest patch level supported is version 6.20 patch 32.

#### Check the Patch Level

1. Open the SAP GUI logon window. Click the top left corner of the SAP Logon dialog box and select **About SAP Logon** from the menu.
2. The SAP version information dialog box opens. Verify that the Patch Level entry is 32 or higher.

#### Check the Kernel Patch Level

1. Log in to the SAP system
2. Select **System > Status**
3. Click the **Other kernel information**  button.
4. In the **Kernel Information** section, check the value of the **Sup. Pkg. lvl.**

The level must be greater than the level listed in the following chart depending on the SAP version you are using.


<b>Software Component</b>	<b>SAP Release</b>	<b>Kernel Patch Level</b>
SAP_APPL	31I	Kernel 3.1I level 650
SAP_APPL	40B	Kernel 4.0B level 903
SAP_APPL	45B	Kernel 4.5B level 753
SAP_BASIS	46B	Kernel 4.6D level 948
SAP_BASIS	46C	Kernel 4.6D level 948
SAP_BASIS	46D	Kernel 4.6D level 948
SAP_BASIS	610	Kernel 6.10 level 360

### Check the R/3 Support Packages

1. Log on to the SAP system and run the SPAM transaction.
2. In the **Directory** section, select **All Support Packages**, and click the **Display** button.
3. Verify that the correct package is installed for your version of SAP according to the table below.

<b>Software Component</b>	<b>Release</b>	<b>Package Name</b>
SAP_APPL	31I	SAPKH31I96
SAP_APPL	40B	SAPKH40B71
SAP_APPL	45B	SAPKH45B49
SAP_BASIS	46B	SAPKB46B37
SAP_BASIS	46C	SAPKB46C29
SAP_BASIS	46D	SAPKB46D17
SAP_BASIS	610	SAPKB61012

If the correct version is installed, a green circle appears in the Status column.




If you do not have the OCS package installed, download it from the [www.sap.com](http://www.sap.com) Web site and install it. For more information, see the SAP OSS note #480149.

## Enable scripting on the SAP Application Server


A user with administrative permissions enables scripting by setting the **sapgui/user\_scripting** profile parameter to **TRUE** on the application server. To enable scripting for all users, set this parameter on all application servers. To enable scripting for a specific group of users, only set the parameter on application servers with the desired access restrictions. The following steps describe how to change the profile parameter.

1. Open transaction **rz11**. Specify the parameter name **sapgui/user\_scripting** and click **Display**. The Display Profile Parameter Attributes window opens.



If **Parameter name is unknown** appears in the status bar, this indicates that you are missing the current Support Package. Import the Support Package that corresponds to the SAP BASIS and kernel versions of the application server, as described in the steps above.

2. If **Profile Val** is FALSE, you need to modify its value. Click the **Change value** button in the toolbar. The Change Parameter Value window opens. Enter TRUE in the **ProfileVal** box and click the **Save** button.



When you save the change, the window closes and **ProfileVal** is set to TRUE.

3. Restart the application server, since this change only takes effect when you log onto the system.

If the updated **ProfileVal** did not change, even after restarting the server, then the kernel of the application server is outdated. Import the required kernel patch, as specified in the steps above.

Note that the Profile Value may be dynamically activated in the following kernel versions, using transaction rz11, without having to restart the application server.


Release	Kernel Version	Patch Level
4.6B, 4.6C, 4.6D	4.6D	972
6.10	6.10	391
6.20	all versions	all levels

### Enable scripting on SAP GUI 6.20 client

To allow VuGen to run scripts, you must also enable scripting on the SAP GUI client. You should also configure the client not to display certain messages, such as when a connection is established, or when a script is attached to the GUI process. The following steps describe how to

configure the SAP GUI client to work with .

1. **During installation.** While installing the SAP GUI client, enable the **SAP GUI Scripting** option.



2. **After installation.** Suppress warning messages. Open the Options dialog box in the SAP GUI client. Select the **Scripting** tab and clear the following options:

- **Notify when a script attaches to a running GUI**
- **Notify when a script opens a connection**

You can also prevent these messages from popping up by setting the values **WarnOnAttach** and **WarnOnConnection** in the following registry key to 0:

`HKCU\SOFTWARE\SAP\SAPGUI_Front\SAP_Frontend_Server\Security`.

## How to Record SAP GUI Scripts

The following steps describe some prerequisites to recording a SAP GUI script.

### Configure the application server for scripting

As a security precaution, scripting is disabled by default. In order to record, you need to enable scripting on the application server. From the RZ11 transaction, set the following profile parameters as follows:

- `sapgui/user_scripting TRUE`
- `sapgui/user_scripting_force_notification FALSE`
- `sapgui/user_scripting_set_READONLY FALSE`
- `sapgui/user_scripting_disable_recording FALSE`

### Close SAPLogon application when recording with Multi

When recording a multi-protocol script in which the SAP GUI client contains Web controls, close the SAPLogon application before recording.

## Use Modal dialog boxes for F1 Help

Instruct the SAP GUI client to open the F1 help in a modal dialog box as follows:


1. Select **Help > Settings**.
2. Click the **F1 Help** tab.
3. Select **in modal dialog box** in the Display section.

## Use Modal dialog boxes for F4 Help

**Note:** This procedure can only be performed by the administrator.

Instruct the SAP GUI client to open the F4 help in a modal dialog box:

1. Make sure that all users have logged off from the server.
2. Select **Help > Settings**. Click the **F4 Help** tab.



3. In the Display section, select **System defaults**.
4. In the Display portion of the System defaults section, select **Dialog**.

5. Save the changes by clicking **Copy initial system setting**.
6. Verify that the status bar displays the message **Data was saved**.
7. Close the session and restart the service through the SAP Management Console.

## How to Replay SAP GUI Scripts

The following steps describe prerequisites to replaying SAPGUI scripts.

### Replace Encrypted Password

Replace the encrypted password in the **sapgui\_logon** function generated during recording, with the real password. It is the second argument of the function, after the following user name

```
sapgui_logon("user", "pswd", "800", "EN");
```

For additional security, you can encrypt the password within the code. Select the password text (the actual text, not \*\*\*\*\*) and select **Encrypt string** from the right-click menu. VuGen inserts an **lr\_decrypt** function at the location of the password as follows:

```
sapgui_logon("user", lr_decrypt("3ea037b758"), "800", "EN");
```

### Display SAP GUI During Replay (optional)

When running a script for the first time, configure VuGen to show the SAP GUI user interface during replay, in order to see the operations being performed through the UI. Select **Replay > Run-Time Settings > SAPGUI > General** node and select **Show SAP Client During Replay**. During a load scenario, disable this option, since it uses a large amount of system resources in displaying the UI for multiple Vusers.

## How to Run SAP GUI Scripts in a Scenario

The following steps describe tips for running SAP GUI scripts in a scenario.

### LoadRunner Controller Settings

When working with a LoadRunner scenario, set the following values when running your script in a load test configuration:

- **Ramp-up.** One by one (to insure proper logon) in the Scheduler.
- **Think time.** Random think time in the run-time settings.
- **Users per load generator.** 50 Vusers for machine with 512 MB of memory in the Load Generators dialog box.

### Make Sure the Agent is Running in Process Mode

Make sure that the LoadRunner (or Performance Center) Remote Agent is running in Process mode. Service mode is not supported.

To check this, move your mouse over the agent's icon in the Windows task bar area, and read the description. If the description reads LoadRunner Agent Service, it is running as a service.



The following steps describe how to restart the agent as a process.

1. Stop the agent. Right-click the LoadRunner Agent icon and select **Close**.
2. Run **magentproc.exe**, located in the **launch\_service\bin** folder, under the LoadRunner installation.
3. To make sure that the correct Agent is launched the next time you start your machine, change the Start type of the Agent Service from Automatic to Manual. Then add a shortcut to **magentproc.exe** to the Windows Startup folder.
  - **Terminal Sessions.** Machines running SAP GUI Vusers may be limited in the number of Vusers that can run, due to the graphic resources available to that machine. To increase the number of Vusers per machine, open additional terminal server sessions on the Load Generator machines. Select **Agent Configuration** from **Start > All Programs > <product\_name> > Advanced Settings**, and select the **Enable Terminal Service** option. You specify the number of terminal sessions in the Load generator machine properties. For more information, see Configuring Terminal Services in the .

**Note:** When the LoadRunner Agent is running in a terminal session, and the terminal session's window is minimized, no snapshots will be captured on errors.

## How to Enhance SAP GUI Scripts

The following steps describe addition options that are available to enhance SAP GUI scripts.

### Record at the Cursor

VuGen allows you to record actions into an existing script by either inserting new actions or replacing existing actions. You may decide to record into an existing script for several reasons:

- You made a mistake in the actions that you performed during recording.
- Your actions were correct, but you need to add additional information such as the handling of popup windows. For example the SAP server may issue an inventory warning, which did not apply during the recording session.

The following steps describe how to record at the cursor.

1. Open the Vuser script in the **Editor** and click in the left margin adjacent to an existing function.
2. Click the **Record at the Cursor** button. VuGen prompts you to make a selection.
3. Select **Insert steps into action** or **Overwrite the rest of the script**.
  - a. **Insert steps into action** inserts the newly recorded steps at the cursor without overwriting

any existing steps. The new segment is enclosed with comments indicating the beginning and end of the added section. This option is ideal for handling occasional popup windows that were not present during the recording.


- b. **Overwrite the rest of the script** replaces all steps from the point of the cursor onward. This option overwrites the remainder of the current Action and deletes all other Actions. It does not affect the **vuser\_init** or **vuser\_end** sections.
4. Click **OK**. VuGen replays the script until the point of the cursor.
5. Wait for the floating recording toolbar to open.
6. Perform the required actions in the SAP GUI client, switching between sections and actions as required.
7. To end the recording session, click the **Stop** button  on the floating toolbar.

## Insert Steps Interactively into a SAP GUI Script


After recording, you can manually add steps to the script in either the **Editor** or **Step Navigator**. In addition to manually adding new functions, you can add new steps interactively for SAP GUI Vusers, directly from the snapshot. Using the right-click menu, you can add object-related steps.

When adding a step from within a snapshot, VuGen uses the Active Screen capability and determines the ID of each object in the SAP GUI client window (unless you disabled Active Screen snapshots in the ["SAPGUI > General Node" on page 240](#)). The following steps describe how to insert a step interactively for a specific object.

1. Verify that you recorded the script when Active Screen snapshots were selected in the SAPGUI General node of the Recording Options (enabled by default).




2. Click within the Snapshot pane.
3. Move the mouse over the object for which you want to add a function. Make sure that VuGen recognizes the object and encloses it with a box.



4. Right-click the object, click **Insert New Step**, and then select a step from the list of steps that

are available for the object.

The step's Properties dialog box opens, with the Control ID of the object when relevant. For example, if you add a **Press Button** step, for the normal center button as shown above, the Properties box displays the following ID:



- Enter a name for the object in the **Description** box. Click **OK**. VuGen inserts the new step after the selected step.

**Note:** You can get the Control ID of the object for the purpose of pasting it into a specific location. To do this, select Copy **Control ID** from the right-click menu. You can paste it into a Properties box or directly into the code from the Script view.

## Add Verification Functions

When working with optional or dynamic windows or frames, you can use verification functions to determine if the window or object is available. An optional window is a window that does not consistently open during the SAP session. This function allows the Vuser script to continue running even if an optional window opens or an exception occurs.

The first example checks if a window is available. If the window is available, the Vuser closes it before continuing.

```
if (!sapgui_is_object_available("wnd[1]"))
    sapgui_call_method("{ButtonID}",
        "press",
        LAST,
        AdditionalInfo=info1011");
sapgui_press_button(.....)
```

The next example illustrates a dynamic object in the ME51N transaction. The Document overview frame is optional, and can be opened/closed by the **Document overview on/off** button.

The code checks the text on the Document overview button. If the text on the button shows Document overview on, we click the button to close the Document overview frame.

```
if(sapgui_is_object_available("tbar[1]/btn[9]"))
{
```

```

sapgui_get_text("Document overview on/off button",
    "tbar[1]/btn[9]",
    "paramButtonText",
    LAST);
if(0 == strcmp("Document overview off", lr_eval_string("{paramButtonText}")))
    sapgui_press_button("Document overview off",
        "tbar[1]/btn[9]",
        BEGIN_OPTIONAL,
        "AdditionalInfo=sapgui1013",
        END_OPTIONAL);
}

```

## Retrieve Information

When working with SAGUI Vusers, you can retrieve the current value of a SAP GUI object using the **sapgui\_get\_<xxx>** functions. You can use this value as input for another business process, or display it in the output log.

The following example illustrates how to save part of a status bar message in order to retrieve the order number.

1. Navigate to the point where you want to check the status bar text, and select **Insert New Step**. Select the **sapgui\_status\_bar\_get\_type** function. This verifies that the Vuser can successfully retrieve text from the status bar.
2. Insert an **if** statement that checks if the previous statement succeeded. If so, save the value of the argument using **sapgui\_status\_bar\_get\_param**.

This **sapgui\_status\_bar\_get\_param** function saves the order number into a user-defined parameter. In this case, the order number is the second index of the status bar string.

```

sapgui_press_button("Save (Ctrl+S)",
    "tbar[0]/btn[11]",
    BEGIN_OPTIONAL,
    "AdditionalInfo=sapgui1038",
    END_OPTIONAL);
sapgui_status_bar_get_type("Status");
if(0==strcmp(lr_eval_string("{Status}"), "Success"))
    sapgui_status_bar_get_param("2", " Order_Number ");

```

During test execution, the Execution log indicates the value and parameter name:

```

Action.c(240): Pressed button " Save (Ctrl+S)"
Action.c(248): The type of the status bar is "Success"
Action.c(251): The value of parameter 2 in the status bar is "33232"

```

## Save Date Information

When creating scripts that use dates, your script may not run properly. For example, if you record the script on June 2, and replay it on June 3, the date fields will be incorrect. Therefore, you need to save the date to a parameter during text execution, and use the stored value as input for other date

fields. To save the current date or time during script execution, use the **lr\_save\_datetime** function. Insert this function before the function requiring the date information. Note that the format of the date is specific to your locale. Use the relevant format within the **lr\_save\_datetime** function. For example, for month.day.year, specify "%m.%d.%Y".

In the following example, **lr\_save\_datetime** saves the current date. The **sapgui\_set\_text** function uses this value to set the delivery date for two days later.

```
lr_save_datetime("%d.%m.%Y", DATE_NOW + (2 * ONE_DAY), "paramDateTo
dayPlus2");
sapgui_set_text("Req. deliv.date",
    "{paramDateTodayPlus2}",
    "usr ctxtRV45A-KETDAT",
    BEGIN_OPTIONAL,
    "AdditionalInfo=sapgui1025",
    END_OPTIONAL);
```

## Additional SAP Resources

For more information, see the SAP website at [www.sap.com](http://www.sap.com) or one of the following locations:

- **SAP Notes** - <https://websmp103.sap-ag.de/notes>

Note #480149: New profile parameter for user scripting on the front end

Note #587202: Drag =; Drop is a known limitation of the SAP GUI interface

- **SAP Patches** - <https://websmp104.sap-ag.de/patches>

SAP GUI for Windows - SAP GUI 6.20 Patch (the lowest allowed level is 32)

## SAP GUI, SAP Web, and SAP (Click & Script) - Troubleshooting and Limitations

This section describes troubleshooting and limitations for SAP GUI, SAP Web, and SAP (Click & Script) protocols.

### General SAP (Click & Script) limitations

- You cannot define transactions to measure time of a subset of steps performed in a modal dialog.
- During recording, if you double-click on a tree-view tree cell outside of its text, VuGen records "Select" instead of "Activate." This results in a missing POST in replay.
- If the list of retrieved values contains a scroll bar, you cannot select an item that requires scrolling in order to retrieve from the server.
- Scalability is lower than the SAP Web protocol, depending on the size and functionality of the business process.

- Does not support the Replace with Alternate Navigation run-time setting.
- In certain SAP environments (such as 6.20 and 6.40), the replay fails for tests that call the **web\_element** function and select an element whose tag name is "TD".
- During recording, if you use a keyboard option instead of a UI element (for example, pressing Enter instead of clicking the log on button), the step may not be recorded. In general, when recording your script, it is recommended to use UI elements rather than keyboard options.

## General SAPGUI limitations

- If a customer business process in SAP GUI 7.30 includes selecting an item from a Combo-list, the business process may not be correctly replayed in LoadRunner versions 9.52 and higher.

**Workaround:** Add the path of the SAP GUI installation folder to the Windows PATH environment variable.

### Question 1: I was able to record a script, but why does replay fail?

Answer: In LoadRunner, make sure that the LoadRunner Remote Agent is running in Process mode. Service mode is not supported. For more information, see "[How to Replay SAP GUI Scripts](#)" on page 789.

### Question 2: Why were certain SAP GUI controls not recorded?

Answer: Some SAP GUI controls are only supported in their menu or toolbar contexts. Try performing the problematic task using a different means—through a menu option, context menu, toolbar, and so on.

### Question 3: Why can't I record or replay any scripts in VuGen?

Answer:

1. Verify that you have the latest patch of SAP GUI 6.20 installed. The lowest allowed patch level is patch 32.
2. Make sure that scripting is enabled. See the "[How to Configure the SAP Environment](#)" on page 782.
3. Verify that notifications are disabled in the SAP GUI for Windows client. Click the Customizing of Local Layout button or press ALT+F12. Click **Options** and select the Scripting tab. Clear both **Notify** options.

### Question 4: What is the meaning of the error popup messages that are issued when I try to run the script?

Answer: Certain SAP applications store the last layout for each user (such as which frames are visible or hidden). If the stored layout was changed since the script was recorded, this may cause replay problems. For Example, in the ME52N transaction, the **Document overview Off/On** button will change the number of visible frames.

If this occurs:

1. Navigate the transaction to the same point as it was during recording, before starting replay. You can use the Snapshot viewer to see the layout in which it was recorded.
2. Add statements to the script that bring the transaction to the desired layout during replay. For example, if an optional frame interferes with your replay, insert a verification function that checks if the frame is open. If it is open, click a button to close it. For verification examples, see "[How to Enhance SAP GUI Scripts](#)" on page 790.

### **Question 5: Can I use the single sign-on mechanism when running a script on a remote machine?**

Answer: No, VuGen does not support the single sign-on connection mechanism. In your SAP GUI client, open the Advanced Options and clear the **Enable Secure Network Communication** feature. Note that you must re-record the script after you modify the Connection preferences.

### **Question 6: Can VuGen record all SAP objects?**

Answer: Recording is not available for objects not supported by SAP GUI Scripting. See your recording log for information about those objects.

### **Question 7: Are all business processes supported?**

Answer: VuGen does not support business processes that invoke Microsoft Office module controls, nor those that require the use of GuiXT. You can disable **GuiXT** from the SAP GUI for Windows client Options menu.

### **Question 8: When I go to the Auto Logon node of the Recording Options, why is the list of server names empty?**

Answer: This sometimes occurs when using SAP GUI Client 7.20. To resolve this issue, copy the **saplogon.ini** file from **%APPDATA%\SAP\Common** where **%APPDATA%** stands for the environment variable specifying the Application Data folder located directly below the user profile folder. Paste the file to the **%WINDIR%** folder (**C:\Windows**).

## **Siebel Web Protocol**

### **Siebel Web Protocol Overview**

The Siebel-Web protocol is similar to the standard Web Vuser protocol, with several changes in the default settings to allow it to work with the Siebel Customer Relationship Management (CRM) application.

You record typical activities in your Siebel session. VuGen records the actions and generates functions with a **web\_** prefix, that emulate your actions.

### **Siebel Web Recording Options and Run-Time Settings**

Before recording a Siebel Web Vuser script, set the following recording options:

- **Recording node:** **HTML-based script**

HTML Advanced - Script type: **A script containing explicit URLs only**

HTML Advanced - Non HTML-generated elements: **Do not record**

- **Advanced node:** Clear the **Reset context for each action** check box.

Before running a Siebel Web Vuser script, set the following run-time setting:

In the Run-Time settings, clear the **Simulate a new user on each iteration** check box in the **Browser Emulation** node.

## How to Record Transaction Breakdown Information

VuGen provides a diagnostic tool for understanding the transaction components in your test—**transaction breakdown**. Using transaction breakdown, you can determine where the bottlenecks are and the issues that need to be resolved.

When preparing your script for transaction breakdown, we recommend that you add think time steps at the end of each transaction using the ratio of one second per hour of testing. For more information about adding think time steps, see "[How to Insert Steps into a Script](#)" on page 406.

In order to record the transaction breakdown information, you need to modify your the parameterization functions in your script.

### Prepare Your Script for Transaction Breakdown

1. Identify the script parameterization replacement of the Session ID.

```
/* Registering parameter(s) from source task id 15
// {Siebel_sn_body4} = "28eMu9uzkn.YGFFevN1FdrCfCC0c8c_"
// */
web_reg_save_param("Siebel_sn_body4",
    "LB/IC=_sn=",
    "RB/IC==;",
    "Ord=1",
    "Search=Body",
    "RelFrameId=1",
    LAST);
```

2. Mark the next **web\_submit\_data** function as a transaction by enclosing it with **lr\_start\_transaction** and **lr\_end\_transaction** functions.
3. Before the end of the transactions, add a call to **lr\_transaction\_instance\_add\_info**, where the first parameter, 0 is mandatory and the session ID has a SSQBLBD prefix.

```
lr_start_transaction("LoginSQLSync");
web_submit_data("start.swe_2",
    "Action=http://design/callcenter_enu/start.swe",
```

```

"Method=POST",
"RecContentType=text/html",
"Referer=http://design/callcenter_enu/start.swe",
"Snapshot=t2.inf",
"Mode=HTML",
ITEMDATA,
"Name=SWEUserName", "Value=wrun", ENDITEM,
"Name=SWEPassword", "Value=wrun", ENDITEM,
"Name=SWERememberUser", "Value=Yes", ENDITEM,
"Name=SWENeedContext", "Value=false", ENDITEM,
"Name=SWEFo", "Value=SWEEntryForm", ENDITEM,
"Name=SWETS", "Value={SiebelTimeStamp}", ENDITEM,
"Name=SWECmd", "Value=ExecuteLogin", ENDITEM,
"Name=SWEBID", "Value=-1", ENDITEM,
"Name=SWEC", "Value=0", ENDITEM,
LAST);
lr_transaction_instance_add_info(0,lr_eval_string("SSQLBD:{Siebel_sn_body4}"))
);
lr_end_transaction("LoginSQLSync", LR_AUTO);

```

**Note:** To avoid session ID conflicts, make sure that the Vusers log off from the database at the end of each session.

## Siebel Web - Troubleshooting and Limitations

This section describes troubleshooting and limitations for Siebel Web Vuser scripts.

### Back or Refresh Error

An error message relating to **Back or Refresh** typically has the following text:

We are unable to process your request. This is most likely because you used the browser back or refresh button to get to this point.

**Cause:** The possible causes of this problem may be:

- The SWEC was not correlated correctly for the current request.
- The SWETS was not correlated correctly for the current request.
- The request was submitted twice to the Siebel server without the SWEC being updated.
- A previous request should have opened a frame for the browser to download. This frame was not created on the server probably because the SWEMethod has changed since the recording.

### Same Values

A typical Web page response to the **Same Values** error is:

@0`0`3`3``0`0`UC`1`Status`Error`SWEC`10`0`1`Errors`0`2`0`Level0`0`ErrMsg`The same values for 'Name' already exist. If you would like to enter a new record, please make sure that the field values are unique.`ErrCode`28591`

**Cause:** The possible cause of this problem may be that one of the values in the request (in the above example, the value of the Name field) duplicates a value in another row of the database table. This value needs to be replaced with a unique value to be used for each iteration per user. The recommended solution is to replace the row ID with its parameter instead insuring that it will be unique.

## No Content HTTP Response

A typical HTTP response for a **No Content HTTP Response** type error is:

HTTP/1.1 204 No Content

Server: Microsoft-IIS/5.0

Date: Fri, 31 Jan 2003 21:52:30 GMT

Content-Language: en

Cache-Control: no-cache

**Cause:** The possible causes of this problem may be that the row ID is not correlated at all or that it is correlated incorrectly.

## Restoring the Context

The typical Web page response to the **Restoring the Context** type error is:

@0`0`3`3``0`0`UC`1`Status`Error`SWEC`9`0`1`Errors`0`2`0`Level0`0`ErrMsg`An error happened during restoring the context for requested location`ErrCode`27631`

**Cause:** The possible causes of this problem may be that the rowid is not correlated or that it is correlated incorrectly.

## Cannot Locate Record

The typical Web page response to the **Cannot locate record** type error is:

@0`0`3`3``0`0`UC`1`Status`Error`SWEC`23`0`2`Errors`0`2`0`Level0`0`ErrMsg`Cannot locate record within view: Contact Detail - Opportunities View applet: Opportunity List Applet.`ErrCode`27573`

**Cause:** The possible causes of this problem may be that the input name SWERowId does not contain a row ID for a record on the Web page. This input name should have been parameterized. The parameter's source value may have changed its location.

## End of File

The typical Web page response to the **End of File** type error is:

@0`0`3`3``0`0`UC`1`Status`Error`SWEC`28`0`1`Errors`0`2`0`Level0`0`ErrMsg`An end of file error has occurred. Please continue or ask your systems administrator to check your application configuration if the problem persists.`ErrCode`28601`

**Cause:** The possible causes of this problem may be that the input name SWERowId does not contain a row ID for a record on the Web page. This input name should have been parameterized. The parameter's source value may have changed its location.

### Unable to Retrieve Search Categories

The typical Web page response to the **Unable to Retrieve Search Categories** type error is:

**Cause:** A possible cause of this problem may be that the search frame was not downloaded from the server. This occurs when the previous request did not ask the server to create the search frame correctly.

## Silverlight Protocol

### Silverlight Protocol - Overview

Microsoft Silverlight is a web application framework that supports graphics, animations, and interactivity. The Silverlight protocol enables you to record applications built with Microsoft Silverlight. The Silverlight protocol includes the Web (HTTP/HTML) protocol as a subset, as well as a number of additional functions, recording options, and run-time settings.

In order to record high level Vuser scripts, you can import WSDL files used by your application in the recording options.

### How to Import WSDL Files

The following steps describe how to import WSDL files into a Silverlight Vuser script, manually or automatically. Alternatively, you can disable WSDL files and generate soap requests. All of these options are performed in the **Silverlight > Services** node of the **Recording Options Dialog Box**. For user interface details, see "["Silverlight > Services Node" on page 240](#)".

#### Automatically Locate WSDL Files

To configure VuGen to automatically detect the WSDL files used by your script and attempt to locate them, select **Use WSDL files included in the script** and **Automatically detect WSDL files and import services during code generation**. If a WSDL is detected that cannot be imported, you will be notified in the Code Generation Notifications box.

#### Manually Locate WSDL Files

You can manually locate WSDL files in a number of ways from the Add Service Dialog Box. To locate a WSDL file whose URL is known, use the **URL** option. If the WSDL file is on your local machine, use the **File** option. To search for the WSDL in the WSDL History (a list of previously imported WSDLs), select **Previously Imported** and click ... to open the list.

For user interface details, see "["Add / Edit Services Dialog Box" on page 241](#)".

#### Disable WSDL Files

You can disable WSDL files and generate SOAP requests instead. This results in a lower level script, however it does increase the performance of your script. To disable WSDL files, select **Do not use WSDL files**.

## Advanced Security Settings

You can modify security and password settings in the Protocol and Security Scenario Data dialog box. For details, see "[Protocol and Security Scenario Data Dialog Box](#)" on page 242.

# Silverlight - Troubleshooting and Limitations

This section describes troubleshooting and limitations for the Silverlight protocol.

- While recording a site developed in Silverlight, the Install Silverlight step is recorded even though recording process did not include installing the Silverlight plug-in.

### Workaround

Configure the run-time settings to exclude the following address:

`http://go.microsoft.com/fwlink/?LinkId=108181`

- a. Select the **Run-Time Settings > Internet Protocol > Download Filters** Node.
- b. Select the **Exclude addresses in list** radio button.
- c. Click **Add** and add `http://go.microsoft.com/fwlink/?LinkId=108181` to the list.

**Note:** The `?LinkId=108181` portion of the URL address may not be static over time and may need to be updated.

- REST services do not generate Silverlight service calls. However they can be recorded and replayed.
- You cannot edit the WSDL location in the Protocol and Security Scenario dialog box.
- The Update button in the Silverlight Service node of the Recording Options dialog box updates the service if the WSDL location has not changed.
- If the WSDL location has changed, the service is re-imported (delete service and import service).
- Duplex (Polling) Binding for WCF Web Services is not supported.
- Silverlight 4 and 5 clients are supported, however applications developed using the new communication features such as net.tcp binding are not supported.
- The VuGen snapshot viewer does not support Silverlight controls.
- The Silverlight Protocol does not support applications which use Japanese, Korean, Simplified Chinese, and Traditional Chinese.

# Web (HTTP/HTML) Protocol

The Web (HTTP/HTML) Vuser protocol is one of LoadRunner's *Web Vuser* protocols. This section includes information that is specific to the Web (HTTP/HTML) Vuser protocol. For information that is generic to all Web Vuser protocols, see "["Web Protocols \(Generic\)" on page 818.](#)

## Web (HTTP/HTML) Protocol - Overview

**Note:** This topic applies to Web (HTTP/HTML) Vuser scripts only.

The Web (HTTP/HTML) Vuser protocol emulates communication between a browser and Web server on an HTTP or HTML level.

**Note:** The Web (HTTP/HTML) Vuser protocol is one of LoadRunner's *Web Vuser* protocols. For a full list of Web Vuser protocols, see "["Web Vuser Types" on page 820.](#)

This topic provides an overview of various topics relating to Web (HTTP/HTML) Vuser scripts.

### When should you use the Web (HTTP/HTML) Vuser protocol?

You can use the Web (HTTP/HTML) Vuser protocol for browser applications that include applets and VB script, and for non-browser applications.

Use the Web (HTTP/HTML) Vuser protocol when the client and the server communication is done over http/s communication, and the complexity of the communication does not require content modification. If content modification is required, consider using the TruClient protocol. For further information about the TruClient protocol, see "["TruClient Protocol " on page 499.](#)

For details on how to select a Vuser protocol, see "["Protocol Advisor - Overview" on page 147.](#)

### Web (HTTP/HTML) Vuser Technology

You use VuGen to develop Web (HTTP/HTML) Vuser scripts. To record a Web (HTTP/HTML) Vuser script, you navigate through a web site - performing typical user activities. VuGen records your actions and generates a Web (HTTP/HTML) Vuser script. The script contains detailed information about the recorded traffic. When you run the script, the resulting Vuser emulates a user accessing the Internet.

For details, see "["Web Vuser Technology" on page 819.](#)

The table below displays a list of the LoadRunner documentation that relates to the process of developing a Web (HTTP/HTML) Vuser script.

Topic	Description
Creating a Web (HTTP/HTML ) Vuser script	See VuGen's generic documentation about creating Vuser scripts [ <a href="#">"Creating Vuser Scripts - Overview" on page 162</a> ].

Topic	Description
Recording	<p>In addition to the generic documentation about recording Vuser scripts [<a href="#">"Recording - Overview" on page 174</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Recording Levels - Overview" on page 252</a></li> </ul> <p><b>Recording Options</b></p> <p>You can configure the following recording options for your Web (HTTP/HTML ) Vuser script:</p> <ul style="list-style-type: none"> <li>• <a href="#">"General &gt; Script Node" on page 203</a></li> <li>• <a href="#">"General &gt; Protocol Node" on page 200</a></li> <li>• <a href="#">"General &gt; Recording Node" on page 200</a></li> <li>• <a href="#">"Network &gt; Port Mapping Node" on page 226</a></li> <li>• <a href="#">"HTTP &gt; Advanced Node" on page 208</a></li> <li>• <a href="#">HTTP &gt; Correlation Node</a></li> <li>• <a href="#">"Data Format Extension &gt; Chain Configuration Node" on page 191</a></li> <li>• <a href="#">"Data Format Extension &gt; Code Generation Node" on page 195</a></li> </ul>
Correlating	<p>In addition to the generic VuGen documentation on correlating Vuser scripts [<a href="#">"Correlation Overview" on page 274</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"How to Correlate Scripts - Web (Manually)" on page 286</a></li> <li>• <a href="#">"Data Format Extensions (DFEs) - Overview" on page 831</a></li> <li>• <a href="#">"Using the LoadRunner JavaScript Engine" on page 806</a></li> </ul>

Topic	Description
Replaying	<p>In addition to the generic VuGen documentation about replaying Vuser scripts [<a href="#">"Replaying - Overview" on page 316</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Browser Emulation - Overview" on page 825</a></li> <li>• <a href="#">"Working with Cache Data" on page 828</a></li> </ul> <p><b>Run-time Settings</b></p> <p>You can configure the following run-time settings for your Web (HTTP/HTML ) Vuser script:</p> <ul style="list-style-type: none"> <li>• General - Run Logic, Pacing, Log, Think Time, Additional Attributes, Miscellaneous</li> <li>• <a href="#">"Network &gt; Speed Simulation Node" on page 371</a></li> <li>• <a href="#">"Browser &gt; Browser Emulation Node" on page 325</a></li> <li>• <a href="#">"Internet Protocol &gt; Proxy Node" on page 363</a></li> <li>• <a href="#">"Internet Protocol &gt; Preferences Node" on page 353</a></li> <li>• <a href="#">"Internet Protocol &gt; Download Filters Node" on page 352</a></li> <li>• <a href="#">"Internet Protocol &gt; ContentCheck Node" on page 351</a></li> </ul>
Debugging	See VuGen's generic documentation about debugging Vuser scripts [ <a href="#">"Debugging - Overview" on page 388</a> ].
Parameterizing	<p>In addition to the generic VuGen documentation on parameterizing Vuser scripts [<a href="#">"Parameterizing - Overview" on page 408</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Data Format Extensions (DFEs) - Overview" on page 831</a></li> <li>• <a href="#">"Using the LoadRunner JavaScript Engine" on the next page</a></li> </ul>
Adding Load Testing functionality	<p>In addition to the generic VuGen documentation on adding load testing functionality [<a href="#">"Enhancing a Script for Load Testing - Overview" on page 395</a>], see:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Text and Image Verification (Web Vuser Scripts) - Overview" on page 820</a></li> </ul>
Viewing Test Results	See VuGen's generic documentation about viewing test results [ <a href="#">"Viewing Replay Results - Overview" on page 480</a> ].

Topic	Description
Misc	<p>The following miscellaneous topics are applicable to Web (HTTP/HTML) Vuser scripts:</p> <ul style="list-style-type: none"> <li>• "<a href="#">"Converting a TruClient Script to a Web HTTP/HTML Script" on page 567</a></li> <li>• "<a href="#">"How to Convert a Web (HTTP/HTML) Vuser Script into a Java Vuser Script" on page 812</a></li> <li>• "<a href="#">"Web Snapshots - Overview" on page 823</a></li> <li>• "<a href="#">"How to record the SPDY protocol" on page 815</a></li> <li>• "<a href="#">"Applications that Use Smooth Streaming" on page 815</a></li> </ul>

## Using the LoadRunner JavaScript Engine

**Note:** This topic applies to Web (HTTP/HTML) Vuser scripts only.

### What is the LoadRunner JavaScript Engine?

Typically, Web (HTTP/HTML) Vuser scripts contain C code. The LoadRunner JavaScript Engine enables you to insert snippets of JavaScript code into the C code.

### What can I do with JavaScript in a Vuser script?

You can insert JavaScript code into a Web (HTTP/HTML) Vuser script to manipulate text strings that are included in the request and response messages that are sent between the client and server. Manipulating strings is often useful for correlation and parameterization purposes. Typical string manipulations include converting decimal to hexadecimal, encoding and decoding Base64, URL encoding and decoding, and accessing object values inside JSON-formatted data.

**Note:** It is possible to perform many of these string manipulation procedures by using LoadRunner's built-in DFEs (Data Format Extensions). For details, see "["Data Format Extensions \(DFEs\) - Overview" on page 831](#).

Inserting JavaScript code into a Vuser script may also be useful when client-side logic is implemented in JavaScript. Inserting snippets of the original client-side JavaScript code into the Vuser script removes the requirement of having to re-write the JavaScript logic into C code to be included in the Vuser script.

You can use JavaScript code in a Vuser script to execute an **XMLHttpRequest**. This allows you to generate and send HTTP or HTTPS requests using standard Javascript APIs. Such APIs include, for example, sending asynchronous requests, assigning callbacks to handle responses, reading responses in XML format. An **XMLHttpRequest** used this way may replace a call to an action step such as **web\_url** or **web\_custom\_request**.

### Why use JavaScript snippets?

Although it may be possible to achieve the required functionality by using C code alone, including JavaScript in a Vuser script may be beneficial for the following reasons:

- JavaScript often offers a more intuitive, easier to implement solution than C.
- The JavaScript regular expression library simplifies the challenge of working with regular expressions.
- There are numerous JavaScript libraries that assist with string manipulation.
- Client-side logic is often implemented in JavaScript. Inserting snippets of the original JavaScript code removes the requirement of having to translate the JavaScript client logic into C code.

### **Can I use the JavaScript Engine in Vuser scripts of all protocols?**

No, the JavaScript Engine enables you to insert JavaScript into Web (HTTP/HTML) Vuser scripts only.

### **What are some scenarios in which the JavaScript Engine may be useful?**

Including JavaScript code in a Vuser script may be useful in the following scenarios:

#### **Scenario 1: Converting a decimal number to its hexadecimal representation**

In this scenario, the response that a Vuser sends to the server must include a 13-digit timestamp in hexadecimal format. For example, the date/time stamp "1234567891234" must be converted by the Vuser into hex and sent as "11F71FB0922". LoadRunner does not include any standard functionality to perform this conversion, and developing the required C code is not trivial. This problem can be resolved by inserting the following JavaScript code into the Vuser script:

```
web_js_run(
  "Code=getHexTimestamp();",
  "ResultParam=HexTS",
  SOURCES,
  "Code=getHexTimestamp=function(){return new Date().getTime().toString(16).toUpperCase();}", ENDITEM,
  LAST);

lr_output_message("[%s]",lr_eval_string("{HexTS}"));
```

#### **Scenario 2: Base64 encoding and decoding**

The request and response messages that are sent between the client and server include data that is encoded using a Base64 coding scheme. Because the data is encoded, it is often difficult or impossible to parameterize or correlate the raw data. The data must be decoded before it can be parameterized or correlated, and then re-encoded before being sent to the server. By including JavaScript snippets in a Vuser script, you can access external JavaScript libraries that implement the required Base64 decoding and encoding functionality.

**Note:** It is possible to implement Base64 decoding and encoding using LoadRunner's built-in Base64 DFE (Data Format Extension). For details, see "["Data Format Extensions \(DFEs\) - Overview" on page 831](#).

## Scenario 3: URL encoding and decoding

In this scenario, the request and response messages that are sent between the client and server include URLs that are encoded using JavaScript URL encoding. By including a JavaScript snippet in a Vuser script, you can access the JavaScript `encodeURI()` and `decodeURI()` functions that perform the required decoding and encoding procedures.

**Note:** It is possible to implement URL decoding and encoding using LoadRunner's built-in URL Encoding DFE (Data Format Extension). For details, see "["Data Format Extensions \(DFEs\) - Overview"](#) on page 831.

## Scenario 4: Accessing objects inside JSON-formatted data

In this scenario, the request and response messages that are sent between the client and server include data in JSON format. To access objects inside the JSON formatted data, you can include a JavaScript snippet inside the Vuser script to access the JavaScript `eval()` function.

**Note:** It is possible to access objects inside JSON-formatted data by using LoadRunner's built-in JSON-To-XML DFE (Data Format Extension). For details, see "["Data Format Extensions \(DFEs\) - Overview"](#) on page 831.

## Scenario 5: Using XMLHttpRequest

You can use JavaScript code in a Vuser script to execute an `XMLHttpRequest` to download stock quotes from a specified site. For an example of how to execute an `XMLHttpRequest`, see "["JavaScript Engine: XMLHttpRequest Example"](#) on page 811.

## Scenario 6: Pre-existing client-side JavaScript code

To access a particular web-site, the Vuser must submit a user name and an encrypted password. The server sends a server hash to the browser to enable the browser to generate the required encrypted password. The code to generate the hash is complicated, and exists in JavaScript. This JavaScript code can be included in the Vuser script, removing the requirement to re-write the JavaScript logic into C code.

### What are the LoadRunner API functions that I can use in a Vuser script to execute Javascript code?

The following LoadRunner API functions are available for including JavaScript in a Vuser script:

1. `web_js_run`: Runs the specified JavaScript code.
2. `web_js_reset`: Clears the JavaScript context.

You use the `web_js_run` function to include JavaScript code in a Vuser script. Using the `web_js_run` function, you can either insert the required JavaScript code into the Vuser script, or you can reference a file that contains the required JavaScript code.

### Example of inserted JavaScript code

The following is an example of how to include JavaScript code directly from the Vuser script:

```
web_js_run(
    "Code=xor((LR.getParam('buffer'), 0xFFFF));",
    "ResultParam=param",
LAST);
```

## Example of a referenced file that contains JavaScript code

The following is an example of how to include JavaScript code by calling a file that contains the JavaScript code:

```
web_js_run(
    "File=XMLHttpRequest_sync_sample.js",
    "ResultParam=param",
LAST);
```

For details on the above functions, and examples of how they can be used, see the Function Reference ([Help > Function Reference](#)).

### Can I use JavaScript to access any "internal" LoadRunner API functions?

JavaScript in a Vuser script gives you access to a number of "internal" LoadRunner API functions that can be called directly from a `web_js_run` function in the JavaScript code. These functions are used primarily for managing parameters, but also enable you to log specified messages, record data, and run `XMLHttpRequest`.

## LoadRunner API functions

API Function	Description	Arguments
<code>LR.advanceParam</code> (parameter)	Advances the specified parameter to the next value in the file.	<b>parameter.</b> The name of the parameter to advance. Must be a parameter of type file or unique number.
<code>LR.setParam</code> (name, value)	Saves a string to a parameter, creating the parameter if it does not exist.	<b>name.</b> The name of the parameter in which to save the value. <b>value.</b> The value.
<code>LR.freeParam</code> (name)	Deletes a dynamic parameter at run-time, freeing its buffer.	<b>name.</b> The parameter name.
<code>LR.getParam</code> (name)	Returns the value of the specified parameter.	<b>name.</b> The parameter name.

API Function	Description	Arguments
LR.log(text, level)	Logs a message.	<p><b>text.</b> The message.  <b>level.</b> One of the following:</p> <ul style="list-style-type: none"> <li>• "Error"</li> <li>• "Warning"</li> <li>• "Standard"</li> <li>• "Extended"</li> <li>• "Status"</li> </ul> <p><b>example:</b> LR.log("text", "Error");</p>
LR.userDataPoint(name, value)	Records a user-defined data point for analysis.	<p><b>name.</b> The name of the data point. Do not begin a data-point name with any of these strings: HTTP, NON_HTTP, RETRY, mic_, stream_, mms_</p> <p><b>value.</b> The numeric value.</p>

### How do I enable the LoadRunner JavaScript Engine?

To run JavaScript from within a Vuser script, the JavaScript Engine must be enabled for the Vuser script. You use the run-time settings to enable the JavaScript Engine.

Click **Replay > Run-Time Settings > Internet Protocol > Preferences > Set Advanced Options - Options > Web JavaScript > Enable Running Java Script Code** and select **Yes**.

**Note:** Enabling this option causes the creation of a Javascript Runtime Engine, even if there are no Javascript steps in the script.

### How do I configure the LoadRunner JavaScript Engine?

You use the Vuser script's run-time settings to configure the LoadRunner JavaScript Engine.

To access the JSE run-time settings, select **Replay > Run-Time Settings > Internet Protocol > Preferences > Set Advanced Options - Options**, and scroll down to the **Web JavaScript** heading.

- **JSE Runtime Size:** Specifies the size of the allocated Javascript Engine Runtime memory, in kilobytes. This value may need to be increased when running large numbers of Vusers.
- **JSE stack size per thread:** Specifies the size of each Vuser thread in the Javascript Engine memory, in kilobytes. This value may need to be increased for large objects or deep stack calls.

For details on the JavaScript Engine run-time settings, see "[Advanced Options Dialog Box](#)" on page 354.

### What is the connection between the JavaScript Engine and LoadRunner's JavaScript Protocol?

There is no connection between the LoadRunner JavaScript Engine and the LoadRunner JavaScript Protocol.

### Troubleshooting

If you encounter difficulties when implementing JavaScript Engine support, review the items below for possible solutions.

1. Make sure that the LoadRunner JavaScript Engine is enabled. For details, see [How do I enable the JavaScript Engine?](#)
2. Memory issues

If the run-time setting **Simulate a new user on each iteration > Clear cash on each iteration** is selected, `web_js_reset` is called automatically at the start of each iteration. If **Simulate a new user on each iteration > Clear cash on each iteration** is not set, avoid excessive memory consumption by inserting `web_js_reset` calls in your Vuser script at points where you no longer need the saved context. For details on the `web_js_reset` function, see the Function Reference ([Help > Function Reference](#)). For details on the run-time settings, see "Browser > Browser Emulation Node" on page 325.

3. Performance issues

If you are experiencing performance issues, you can modify the Web JavaScript run-time settings. For details, see "[Advanced Options Dialog Box](#)" on page 354.

## JavaScript Engine: XMLHttpRequest Example

**Note:** This topic applies to Web (HTTP/HTML) Vuser scripts only.

The LoadRunner JavaScript Engine enables you to include JavaScript code in a Vuser script. For details on the JavaScript Engine, see "[Using the LoadRunner JavaScript Engine](#)" on page 806.

The example below shows how you can use a JavaScript **XMLHttpRequest** object in a Web (HTTP/HTML) Vuser script. In this example, the **XMLHttpRequest** object enables the Vuser to download a stock quote from finance.example.com, and then to save the value to a parameter for future use.

The script section below shows a `web_js_run` function that has been inserted into a Vuser script. The `web_js_run` function includes a reference to a file called `XMLHttpRequest_sync_sample.js`. This file contains the JavaScript code that executes the `XMLHttpRequest` function.

```
web_js_run(
  "Code=getQuotes(LR.getParam('symbol'))",
  "ResultParam=param",
  SOURCES,
  "File=XMLHttpRequest_sync_sample.js", ENDITEM,
  LAST);
```

The contents of the XMLHttpRequest\_sync\_sample.js file are shown below.

```

var req2;

function getQuotes(mySymbol)
{
    var myURL="http://download.finance.example.com/d/quotes.csv?s="+mySymbol+"&f=l1&e=.csv";

    req2=false;
    // branch for native XMLHttpRequest object
    try {
        req2=new XMLHttpRequest();
    } catch(e) {
        req2=false;
    }
    if(req2) {
        req2.open("GET", myURL, false);
        req2.send("");
    }
    return req2.responseText;
}

```

- For additional examples of code used with the JavaScript Engine, see the Function Reference ([Help > Function Reference](#)).
- For information about the **XMLHttpRequest** object, see [http://www.w3schools.com/ajax/ajax\\_xmlhttprequest\\_send.asp](http://www.w3schools.com/ajax/ajax_xmlhttprequest_send.asp).

## How to Convert a Web (HTTP/HTML) Vuser Script into a Java Vuser Script

**Note:** This topic applies to Web (HTTP/HTML) and Java Vuser scripts only.

VuGen provides a utility that enables you to convert a Web (HTTP/HTML) Vuser script into a Java Vuser script. This also allows you to create a hybrid Vuser script for both Web and Java.

How to convert a Web (HTTP/HTML) Vuser script into a Java Vuser script

1. Create an empty **Java Vuser** script and save it.
2. Create an empty **Web (HTML/HTTP)** Vuser script and save it.
3. Record a session into the Web (HTML/HTTP) Vuser script.
4. Replay the Web (HTML/HTTP) Vuser script. When it replays correctly, cut and paste the entire script into a text editor and save it as a text file (.txt).  
In the text file, modify any parameter braces from the Web type, "{ }" to the Java type,

"< >".

5. Open a DOS command window and go to the <LoadRunner Installation> / **dat** folder.

6. Type the following command:

```
<LoadRunner_Installation Folder>\bin\sed -f web_to_java.sed filename > outputfilename
```

where **filename** is the full path and filename of the text file you saved earlier, and **outputfilename** is the full path and filename of the output file.

7. Open the output file, and copy its contents into your Java Vuser script action section at the desired location.

If you are pasting the contents into an empty custom Java template (Java Vuser type), modify the line containing `public int action()` as follows:

```
public int action() throws Throwable
```

This change is done automatically for recorded Java users (RMI and CORBA).

8. Parameterize and correlate the Vuser script as you would with an ordinary Java script, and run the script.

## How to create a script for a REST API

In recent years, Representational State Transfer (REST) has become a popular model for software architecture, especially for Web-based applications. Today, most large websites such as Twitter, Google, Flickr, and so forth, use REST APIs. Using LoadRunner's **web\_custom\_request** function, you can create a load test script for a REST API.

A REST API call consists of the following components:

- **Uniform Resource Identifier (URI).** A string comprised of the host, the path of the functional component, and the Query string, with key-value pairs. For example  
`http://www.shopping.hp.com/en_US/home-office/-/products/Tablets/Tablets?SearchParameter=ElitePad`
- **Action.** The action to perform, such a GET, POST, PUT, DELETE, and PATCH.
- **Data.** The data to send to the server, usually in JSON format.

All of these components are included as parameters of a **web\_custom\_request** function.

This tasks describes how to create script steps for a Web (HTTP/HTML) script that calls a REST API.

1. Create a Web (HTTP/HTML ) Vuser script. For details see, "["Creating Vuser Scripts - Overview" on page 162.](#)
2. Record the REST API application. Perform typical business processes in your application.
3. After you finish recording, add new **web\_custom\_request** calls using the following format:
 

```
web_custom_request("<Step_Name>",
"URL=<URI of the REST API>",
"Method=<Action>",
"Resource=0",
"EncType=application/json",
"Mode=HTTP",
"Body=<Body text in JSON format>,
LAST);
```
4. If you want to reference a file with the JSON data instead of entering the actual text, follow these steps:
  - a. In the Solution Explorer, right-click the **Extra Files** node and select **Add Files to Script** to add the .json data file.
  - b. Replace the **Body** argument with **BodyFilePath=<file\_name.json>**.
  - c. Allow JSON files. Select **Tools > Options > Scripting > Script Management** and add .json to the Allowed Extensions list.

## Examples

The following example shows a REST API function that updates values using a PUT action:

```
web_custom_request("Update My App",
"URL=http://localhost:3000/MyRESTAPI/3",
"Method=PUT",
"Resource=0",
"EncType=application/json",
"Mode=HTTP",
"Body={"id":3,
"isFinished":false,"MyText":"Updated name"},
LAST);
```

The next example shows a REST API function that updates values using a POST action, using data from a file:

```
web_custom_request("Update My App",
"URL=http://localhost:3000/MyRESTAPI/3",
"Method=POST",
"Resource=0",
```

```
"EncType=application/json",
"Mode=HTTP",
"BodyFilePath=data.json",
LAST);
```

## How to record the SPDY protocol

SPDY is an open networking protocol for transporting web content. The goal of SPDY is to reduce web page load time. The transport is SSL (HTTPS). SPDY does not replace HTTP rather, it modifies the way HTTP requests and responses are sent.

This task describes how to record a Web (HTTP/HTML) script that uses the SPDY protocol.

1. Create a Web (HTTP/HTML) Vuser script. For details see, ["Creating Vuser Scripts - Overview" on page 162](#).
2. Select **Recording Options > Network > Port Mapping > Options > TLS NPN** to enable the recording of the SPDY protocol.
3. Click the **Start Record** button. In the Start Recording dialog box, select a browser. **Note:** If you are recording on Chrome, make sure all other instances of Chrome are closed before you begin the recording.
4. Start recording and perform typical business processes on your application.

## Applications that Use Smooth Streaming

This task explains how to record applications that use Smooth Streaming.

### What is Smooth Streaming?

Smooth Streaming is an Internet Information Services (IIS) Media Services extension which provides streaming of high-quality video to clients over HTTP. Smooth Streaming adapts the stream rate and quality by monitoring the local bandwidth and video playback performance of the client while traditional streaming delivers the content at a fixed rate and quality.

### How to prepare a script for load testing for applications that use Smooth Streaming:

1. Create a Web (HTTP/HTML) Vuser script. For details see, ["Creating Vuser Scripts - Overview" on page 162](#).
2. Look for the “Manifest” request at the start of the streaming communication:

```

web_custom_request("Manifest",
    "URL=http://mediadl.microsoft.com/mediadl/iisnet/smoothmedia/E
xperience/BigBuckBunny_720p.ism/Manifest",
    "Method=GET",
    "Resource=0",
    "RecContentType=text/xml",
    "Referer=",
    "Snapshot=t11.inf",
    "Mode=HTTP",
    LAST);

```

3. Following the “Manifest” request, you should find a number of streaming requests:

```

web_custom_request("Fragments (video=0)",
    "URL=http://mediadl.microsoft.com/mediadl/iisnet/smoothmedia/E
xperience/BigBuckBunny_720p.ism/QualityLevels(350000)/Fragments(video=
0)",
    "Method=GET",
    "Resource=1",
    "RecContentType=video/mp4",
    "Referer=",
    "Snapshot=t12.inf",
    LAST);

web_custom_request("Fragments (audio=0)",
    "URL=http://mediadl.microsoft.com/mediadl/iisnet/smoothmedia/E
xperience/BigBuckBunny_720p.ism/QualityLevels(64000)/Fragments(audio=0
)",
    "Method=GET",
    "Resource=1",
    "RecContentType=video/mp4",
    "Referer=",
    "Snapshot=t13.inf",
    LAST);

```

Create and configure parameters to emulate different bandwidths than the ones that were recorded.

For example:

- a. In the streaming request, replace QualityLevel with a parameter named 'qualityLevel'.

```
| web_custom_request("Fragments(video=0)",
    "URL=http://mediadl.microsoft.com/mediadl/iisnet/smoothmedia/E
xperience/BigBuckBunny_720p.ism/QualityLevels({qualityLevel})/Fragment
s(video=0)",
    "Method=GET",
    "Resource=1",
    "ReqContentType=video/mp4",
    "Referer=",
    "Snapshot=t12.inf",
    LAST);
```

- b. Configure the 'qualitylevel' values that will be used during each iteration of the load test in the ["Parameter Properties Dialog Box" on page 426](#).
4. Replay the script and verify that the size of the response from each request corresponds to the value of the parameter that was sent.

## Converting a TruClient Script to a Web HTTP/HTML Script

Combine the advantage of fast script development and the advantage of running many Vusers by converting a TruClient script to a Web HTTP/HTML script.

**Note:** You will need to have an understanding of the Web HTTP/HTML protocol to successfully replay the script.

1. Create a TruClient script. For details, see ["How to Develop TruClient Scripts" on page 511](#)
2. Save the script and close the TruClient Side Bar.
3. From VuGen toolbar, click the **Convert** button on the toolbar to open the Convert TruClient Script to Web-HTTP/HTML Script dialog box.
4. Specify a script name and location or accept the default values. Click **Convert**.
5. After the script is generated, review it, keeping in mind that the Web HTTP/HTML protocol records on the transport level. For example, you may need to address correlation or parameter issues in your converted script. For details, see ["Web \(HTTP/HTML\) Protocol - Overview" on page 803](#)

### Limitations

Conversion of TruClient scripts to Web HTTP/HTML scripts does not support converting steps that call 127.0.0.1 (localhost) address.

# Troubleshooting and Limitations - Web (HTTP/HTML) Protocol

This section describes troubleshooting and limitations for the Web (HTTP/HTML) protocol.

- Port mapping configurations is not supported in the Proxy Recording mode.
- VuGen cannot get a client certificate from Internet Explorer 10 while recording a session.  
**Workaround:** Provide a client certificate in the port mapping settings.
- When strong private key protection is set on a certificate and the WinInet mode is used during the replay, you may be required to manually enter authentication details when replaying the script.
- In previous versions of LoadRunner, the C type "char" was considered a "signed char". In LoadRunner 11.50 and later, it is considered as an "unsigned char". If you used "char" without specifying whether it is signed or unsigned, and performed arithmetic operations on this variable, then the results may be different when comparing current results with those from previous versions of LoadRunner.

## Web Protocols (Generic)

The **Web Protocols** section includes information that is generic to all Web Vuser protocols. For information that is specific to a given Web Vuser protocol, see the documentation for that specific protocol.

## Web Protocols - Overview

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" on page 820.

You use VuGen to develop Web Vuser scripts. While you navigate through a site performing typical user activities, VuGen records your actions and generates a Vuser script. When you run the script, the resulting Vuser emulates a user accessing the Internet.

Suppose you have a web site that displays product information for your company. The site is accessed by customers and potential customers. You want to make sure that the response time for any customer query is less than a specified value (for example, 20 seconds)—even when many users (for example, 200) access the site simultaneously. You use Vusers to emulate this scenario, where the web server services simultaneous requests for information. Each Vuser could do the following:

- Load the home page
- Navigate to the page containing the product information

- Submit a query
- Wait for a response from the server


You can distribute several hundred Vusers among the available testing machines, each Vuser accessing the server by using its API. This enables you to measure the performance of the server under the load of many Vusers.

For more details about Web Vuser scripts, see "[Web Vuser Technology](#)" below.


## Web Vuser Technology

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" on the next page.

Vugen creates Web Vuser scripts by monitoring and recording the web traffic that flows between a web browser and a web server while you perform typical business processes. The web traffic includes HTTP requests sent by the browser to the server, and the HTTP responses returned by the server.



When you run a Web Vuser script, the resulting Vuser communicates directly with the web server without relying on a browser or client software. To perform this communication, the Vuser script sends web API functions directly to the web server.



## Web Vuser Types

LoadRunner enables you to build and run web-based Vuser scripts using a variety of Web Vuser protocols. Following is a list of LoadRunner's Web Vuser protocols:

- Ajax (Click & Script)
- Flex
- Java over HTTP
- Oracle Web Applications 11i
- SAP (Click & Script)
- SAP – Web
- Siebel – Web
- Silverlight
- TruClient - Ajax
- Web (HTTP/HTML)

## Text and Image Verification (Web Vuser Scripts) - Overview

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" above.

VuGen enables you to add checks to your Web Vuser scripts. A check verifies the presence of a specific object in a Web page. The object can be either a text string or an image.

Checks enable you to determine whether or not your Web site is functioning correctly while it is being accessed by many Vusers—that is, does the server return the correct Web pages? This is particularly important while your site is under the load of many users, a period when the server is more likely to return incorrect pages.

For example, assume that your Web site displays information on the temperatures in major cities around the world. You use VuGen to create a Vuser script that accesses your Web site.

The Vuser accesses the site and executes a text check on this web page. For example, if the word **Temperature** appears on the page, the check passes. If **Temperature** does not appear because, for example, the correct page was not returned by the server, the check fails. Note that the text check step appears before the URL step. This is because VuGen registers, or prepares in advance, the search information relevant for the next step. When you run the Vuser script, VuGen conducts the check on the web page that follows.



Although the server may display the correct page when you record the script and when a single Vuser executes the script, it is possible that the correct page will not be returned when the server is under the load of many Vusers. The server may then be overloaded and may therefore return meaningless or incorrect HTML code. Alternatively, in some instances when a server is overloaded, the server returns a **500 Server Error** page. In both of these cases, you can insert a check to determine whether or not the correct page is returned by the server.

**Note:** Checks increase the work of a Vuser, and therefore you may be able to run fewer Vusers per load generator. You should use checks only where experience has shown that the server sometimes returns an incorrect page.

- For more details, see "[Understanding Web Text Check Functions](#)" below.
- For details on how to add a text check or an image check, see "[How to Add Text Checks and Image Checks \(Web Vuser Protocols\)](#)" on the next page.

## ***Understanding Web Text Check Functions***

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" on the previous page.

When you add a text check to a Web Vuser script, VuGen adds a **web\_reg\_find** function to the script. This function registers a search for a text string in an HTML page. Registration means that the Vuser does not execute the search immediately—rather the Vuser performs the check only after executing the next Action function, such as **web\_url**.

**Note:** If you are working with a concurrent functions group, the **web\_reg\_find** function is executed only at the end of the grouping.

In the following example, the **web\_reg\_find** function searches for the text string "Welcome". If the string is not found, the next action function fails and the script execution stops.

```

web_reg_find("Text=Welcome", "Fail=Found", LAST);
web_url("Step", "URL=...", LAST);
  
```

In addition to the **web\_reg\_find** function, you can use other functions to search for text within an HTML page:

Several additional functions can be used for searching for text:

- **web\_find**

- `web_global_verification`

The `web_find` function, primarily used for backward compatibility, differs from the `web_reg_find` function in that `web_find` is limited to HTML-based scripts (see **Recording Options > Recording** tab). It also has less attributes, such as `instance`, allowing you to determine the number of times the text appeared. When performing a standard text search, `web_reg_find` is the preferred function.

The `web_global_verification` function allows you to search the data of an entire business process. In contrast to `web_reg_find`, which only applies to the next Action function, this function applies to all subsequent Action functions such `web_url`. By default, the scope of the search is `NORESOURCE`, searching only the HTML body, excluding headers and resources.

The `web_global_verification` function is ideal for detecting application level errors that are not included the HTTP status codes. This function is not limited to an HTML-Based script (see **Recording Options > Recording** tab).

## **How to Add Text Checks and Image Checks (Web Vuser Protocols)**

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" on page 820.

There are a number of different types of checks that you can add to your Web Vuser scripts. For background information, see "[Text and Image Verification \(Web Vuser Scripts\) - Overview](#)" on page 820.

### **How to Add a Text Check While Recording**

1. In the web browser, select the desired text.
2. Click the **Insert Text Check** button  on the VuGen Recording toolbar. VuGen adds a `web_reg_find` function to the script.

### **How to Add a Text Check After Recording**

1. In the Snapshot pane, display a snapshot that contains the text you want to verify.
2. In the Snapshot pane toolbar, click **HTTP Data** to display the HTTP Data view of the snapshot.
3. In the snapshot, select the text you want to verify. The text must be located in a response section of the snapshot - not in a request section.
4. Right-click and select **Add Text Check Step** from the menu.
5. Modify the options in the Find Text dialog box. For details on the dialog box options, press F1 when in the dialog box to open the Function Reference.

6. Click **OK** to insert the function into the Vuser script.

## How to Add Other Text Checks After Recording

1. In the script editor, locate the position where you want to insert the check.
2. Select **View > Toolbox** to open the Toolbox.
  - a. To insert a **web\_reg\_find** function, in the Toolbox, under **Services**, select **web\_reg\_find**.
  - b. To insert a **web\_global\_verification** function, in the Toolbox, under **Services**, select the required **web\_global\_verification** function.
3. Drag the selected function to the required location in the Editor.
4. Enter the required details in the dialog box that opens. For details on the dialog box options, press F1 when in the dialog box to open the Function Reference.
5. Click **OK** to insert the function into the Vuser script.

## How to Add an Image Check After Recording

1. In the Editor, locate the position where you want to insert the check.
2. Select **View > Toolbox** to open the Toolbox.
3. In the Toolbox, under **Web Checks**, select **web\_image\_check**.
4. Drag the selected **web\_image\_check** function to the required location in the Editor.
5. Enter the required details in the Image Check Properties dialog box. For details on the dialog box options, press F1 when in the dialog box to open the Function Reference.
6. Click **OK** to insert the function into the Vuser script.

# Web Snapshots - Overview

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "["Web Vuser Types" on page 820](#).

Web Vuser scripts use VuGen's Snapshot pane.

- For an introduction to the Snapshot pane, see "[Snapshot Pane - Overview](#)" on page 85.
- For details on how to work with the Snapshot pane, see "[How to Work with Snapshots](#)" on page 88.
- For details on the Snapshot pane UI, see "[Snapshot Pane](#)" on page 126.

The snapshots show detailed information about some of the steps in the Vuser script. Each snapshot can be displayed using either the **Page** view or the more detailed **HTTP Data** view.

The HTTP Data view displays each HTTP transaction in either a tree view or a grid view. The transaction data is broken up into response data, request data, headers, cookies, and query strings.

The screenshot shows the HP LoadRunner interface with the 'Snapshot' pane open. At the top, there's a toolbar with buttons for Single, Split, Horizontal, Vertical, Recording, Replay, Http Data, Page View, Tree, and Grid. Below the toolbar is a grid table showing three transactions:

Path	Start Time	Response Time [mse]	
http://datafeed.weatherbug.com/GetXml.aspx?Partne	4:31:37.580	437	15.191.1
http://welcome.hp-ww.com/country/us/en/cs/system/s	4:31:38.454	15	15.191.1
http://welcome.hp-ww.com/country/us/en/cs/system/s	4:31:38.578	16	15.191.1

Below the grid, there are tabs for Raw Data, Request Body, Response Body, Headers, Cookies, and Query String. The Request tab shows the following details:

```

GET http://datafeed.weatherbug.com/GetXml.aspx?PartnerID=1&CityID=1&Unit=M
Accept: */*
Accept-Encoding: gzip, deflate
User-Agent: Mozilla/4.0 (compatible; MSIE 8.0; Windows NT 6.1; Trident/4.0; SLCC2; .NET CLR 2.0.50727; .NET CLR 3.5.30729; .NET CLR 3.0.30729; Media Center PC 6.0; .NET4.0C; .NET4.0E)
Host: datafeed.weatherbug.com
Proxy-Connection: Keep-Alive
  
```

The Response tab shows the following details:

```

HTTP/1.1 200 OK
Content-Type: text/xml; charset=utf-8
Server: Microsoft-IIS/7.5
X-AspNet-Version: 4.0.30319
X-Powered-By: ASP.NET
Cache-Control: private, max-age=120
Date: Sun, 01 Apr 2012 09:45:10 GMT
Content-Length: 117
Proxy-Connection: Keep-Alive
Connection: Keep-Alive
  
```

On the right side of the pane, there are buttons for TextView and HexView.

Data in the snapshots can be displayed in a number of formats: Data view, Text view, and Hex view.

You can split the Snapshot pane to display two snapshots - typically a record snapshot and the corresponding replay snapshot. If both snapshots are displayed in the HTTP Data view, you can click the Sync button on the Snapshot pane toolbar to synchronize the data that is displayed in the two snapshots. For details, see "[How to Work with Snapshots](#)" on page 88.

Correlations and parameters can be created on response data by selecting the desired text and right-clicking.

For data that is difficult to work with (such as binary data), VuGen offers a variety of Data Format Extensions that can transform certain data types into more readable formats. Data that has been

formatted by a Data Format Extension can be displayed in its original or formatted state. For more information, see ["Data Format Extensions \(DFEs\) - Overview" on page 831](#).


## Browser Emulation - Overview

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see ["Web Vuser Types" on page 820](#).


When you run a Web Vuser that accesses a web-site, the Vuser does not use an actual browser to access the site. Instead, the Vuser *emulates* a browser accessing the site. To enable the emulation, the Vuser uses a user-agent string.

### What is a User-Agent String?

When a browser sends a request to a server, the browser sends a **user-agent string** that identifies itself to the server. The identifying details in the user-agent string are included in various **tokens**. These tokens provide various details such as which browser is being used, the version of the browser, and the operating system on which the browser is running.



The user-agent string is included in a **User-Agent** header that is part of every request that is sent by the browser to the server. Servers can use the information that is contained in the user-agent string to provide content that is tailored for the specific browser.



Below is an example of a User-Agent header that contains a user-agent string that is sent to a server. In this example, the user-agent string identifies the browser as Internet Explorer 7.0, running under Windows 7.

**User-Agent:** Mozilla/4.0 (compatible; MSIE 7.0; Windows NT 6.1)

### Emulating a specific browser

When you run a Web Vuser that accesses a web-site, the Vuser *emulates* a browser accessing the site. To enable the emulation, the Vuser creates a user-agent string that includes various tokens.

- The *Browser* and *Version* tokens define the browser to emulate and the version of the emulated browser.
- The *Platform* token defines the operating system on which the emulated browser is running.
- The *Language* token defines the language for which the emulated browser is localized.

The user-agent string is included in a **User-Agent** header in every request that the Vuser sends to the server that hosts the web-site.

### What information is included in Web Vuser's user-agent string?

1. When a Vuser script is first created, the browser in the user-agent string is Internet Explorer 6, and the operating system is Windows.
2. After the code in a Vuser script is generated, the browser in the user-agent string is changed to the browser that was used when the script was recorded, and the operating system is changed to the operating system that was used when the script was recorded.

After the code in a Vuser script is generated, you can use the Vuser script's run-time settings to specify an emulated browser that is different from the browser that was used when the script was recorded. There are scenarios in which this enables you to more accurately emulate the real-world situation. When you specify the emulated browser, you can specify the browser type and version, the platform on which the Vuser runs, and the language for which the browser is localized. VuGen creates a user-agent string that includes the details that you specify. If required, you can edit the user-agent string to create a customized user-agent string.

### Specifying a specific browser to emulate

To specify an emulated browser that is different from the browser that was used when the script was recorded:

1. Open the Vuser script.
2. Click **Replay > Run-Time Settings**.
3. In the Run-Time Settings dialog box, click **Browser > Browser Emulation**, and then select **Use Browser**.
4. Select from the lists of available options to specify the browser to emulate.

**Note:** The **User-Agent String** that is displayed is updated after each selection that you make.

### Customizing the user-agent string

You can customize the user-agent string as follows:

1. Open the Vuser script.
2. Click **Replay > Run-Time Settings**.
3. In the Run-Time Settings dialog box, click **Browser > Browser Emulation**, and then select **Use Custom**.
4. Modify the user-agent string as required.

#### Maximum number of concurrent connections

When a browser accesses a web-site, the browser maintains a number of concurrent connections with the web server that hosts the web-site. Therefore, when you access a web page that contains many different objects, such as images, Javascript files, frames, data feeds etc, the browser may try to improve performance by downloading several of the objects simultaneously. The maximum number of concurrent connections is dependent on the browser type, and the version of the browser. For example, Internet Explorer 6 limits the number of concurrent connections to 2; Internet Explorer 8 and Firefox 3+ limit the number of concurrent connections to 6.

#### Defining the maximum number of concurrent connections for a Vuser

When you run a Web Vuser, by default, the maximum number of concurrent connections that the Vuser can maintain with a web-server is defined by the browser that is specified in the Vuser script's user-agent string. However, you can use the **MAX\_CONNECTIONS\_PER\_HOST** option in the **web\_set\_sockets\_option** function to override the default value. For details, see the Function Reference (**Help > Function reference**).

The following example sets the maximum number of concurrent connections to 10:

```
web_set_sockets_option("MAX_CONNECTIONS_PER_HOST", "10");
```

**Note:** When you run a Web Vuser script, the maximum number of concurrent connections that the Vuser can maintain with the server appears in the Replay log.

## How to Perform Load Testing with nCipher HSM

This task describes how to set up a script to load test an environment with an nCipher HSM (Hardware Security Module).

### 1. Prerequisite

Generate the client certificate file (client\_cert.pem) with the private key (client\_key.pem) pointing to the private keys stored in the HSM. Make sure that you can connect to your Web server (A.com) with a generated CA file (ca-certs.pem). The successful OpenSSL command should have the following form:

```
openssl s_client -connect A.com:443 -CAfile ca-certs.pem -cert client_cert.pem -certform PEM -key client_key.pem -keyform PEM -engine CHIL
```

## 2. Set up the PATH environment variable

Add the **nfhwcrhk.dll** file, usually located in c:\Program Files (x86)\nCipher\ncfast\toolkits\hwcrhk, to the PATH environment variable. Restart VuGen in order for the change to take affect.

## 3. Enable nCipher key retrieval

In the Advanced Run-Time Settings, set **Enable retrieving keys from nCipher HSM** to Yes. For details, see "[Advanced Options Dialog Box](#)" on page 354.

## 4. Edit the Vuser script

Add the following content to the **vuser\_init** section of your Vuser script.

```
web_set_sockets_option(SSL_VERSION, "TLS");
web_set_sockets_option(DEFAULT_VERIFY_PATH, <full_path>\ca-certs.pem);
web_set_certificate_ex (
    "CertFilePath=<full_path_to_client_cert_file>/client_cert.pem",
    "CertFormat=PEM",
    "KeyFilePath= <full_path_to_client_private_key_file> /client_key.pem",
    "KeyFormat=PEM",
    LAST);
```

# Working with Cache Data

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" on page 820.

Web browsers maintain a cache of objects that have been downloaded by the browser. When accessing a website, if any of these objects are required, the browser may use the objects directly from the cache, and not have to download the objects again. This enables the required pages to be loaded quicker. When you run a Vuser script, by default, the Vuser starts with an empty cache. This implies that the Vuser must download each object the first time that the object is required. To better emulate a real-world situation, you can provide the Vuser with a pre-defined cache at any stage while the Vuser is running. The Vuser can then access required objects directly from the cache, without having to download them. To provide a Vuser with a pre-defined cache, first you create a file

that contains the cache, and then you load the cache into the Vuser. You use the **web\_dump\_cache** function to create the cache file, and the **web\_load\_cache** function to load the cache file into the Vuser.

- For details on the cache functions, see the *Function Reference (Help > Function Reference)*.
- For details on how to implement the cache functions, see "[How to Insert Caching Functions](#)" on the next page.

## Creating the cache file

You use the **web\_dump\_cache** function to create a cache file. The **web\_dump\_cache** function creates a file that contains all the objects that exist in the Vuser cache when the **web\_dump\_cache** function is executed. Insert the **web\_dump\_cache** function into a Vuser script, typically towards the end of the *Action* section of the script. This will ensure that the Vuser cache contains the required objects when the **web\_dump\_cache** function is run to create the cache file. After inserting the **web\_dump\_cache** function, run the script to build the Vuser cache and create the cache file.

**Note:** You need to run the **web\_dump\_cache** function only once to generate the required cache file. Typically, this run is not part of a scenario. After the cache file has been created, when you run the Vuser script as part of a scenario, there is no need to execute the **web\_dump\_cache** function. Therefore you should comment-out the **web\_dump\_cache** function in the Vuser script.

You use the **FileName** argument in the **web\_dump\_cache** function to specify the name and location of the file to create. The **FileName** path can be either absolute (e.g. "FileName=c:\\MyDir\\User1.cache") or relative to the current Vuser directory (e.g. "FileName=Iteration1.cache").

- **Absolute path names:** Use absolute path names if you do not want the cache file to be linked to the script. For example, if you wish to use a different cache on each host, use an absolute path.
- **Relative path names:** If you use a relative path name, the cache file is created inside the Vuser directory. When you copy the Vuser script, save it to a new location, or copy it to a load generator host, the cache file is also copied. Relative paths are independent of drive mappings and network locations.

The file extension of the cache file is always ".cache". The ".cache" extension is added if it is not specified in the **FileName** argument. For example, if you specify "FileName=Iteration2.txt", the cache file is called "FileName=Iteration2.txt.cache".

File names in the **FileName** argument can be parameterized so that different Vusers or different iterations can use different cache files. For example, "FileName=Iteration{param}.cache"

In the following example, the **web\_dump\_cache** function creates a cache file for each **VuserName** parameter running the script. The cache files are located in c:\\temp.

```
web_dump_cache("paycheckcache","FileName=c:\\temp\\{Vuser
```

```
Name}paycheck", "Replace=yes", LAST)
```

If you run a single Vuser user ten times, VuGen creates ten cache files in the following format, where the "Kunnn" prefix is the VuserName value:

```
Ku001paycheck.cache  
Ku002paycheck.cache  
Ku003paycheck.cache  
...
```

### Loading the cache file into a Vuser

The **web\_load\_cache** function loads a cache file into a Vuser. The **FileName** argument in the **web\_load\_cache** function specifies the name and location of the cache file to load. The specified cache file must exist before the **web\_load\_cache** function is executed. Therefore, you can run the **web\_load\_cache** function only after running the **web\_dump\_cache** function to create the cache file.

In the following example, the **web\_load\_cache** function loads the **{VuserName}paycheck** cache files from **c:\temp**.

```
web_load_cache("ActionLoad","FileName=c:\\temp\\{VuserName}paycheck",LAST)
```

## How to Insert Caching Functions

**Note:** This topic applies to Web Vuser protocols only. For a list of Web Vuser protocols, see "[Web Vuser Types](#)" on page 820.

This task describes how to use caching functions. Caching functions allow you to create a cache file that contains the Vuser cache, and then to load the cache file data into a Vuser. For more information, see "[Working with Cache Data](#)" on page 828. The following steps describe how to use the caching functions.

1. Insert the **web\_dump\_cache** function into your Vuser script.
2. Run the script to create the cache file.
3. Insert the **web\_load\_cache** function into your script - before the Vuser actions.
4. Comment-out the **web\_dump\_cache** function.
5. Run and save the script.

For details on the caching functions, see the *Function Reference (Help > Function Reference)*.

# Data Format Extensions (DFEs) - Overview

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

**Definition:** Data Format Extension support - or DFE support for short - enables easier scripting of web applications by providing the ability to decode and encode formatted data that is exchanged between the client and the server. This enables easier correlation and parameterization of the generated Vuser scripts.

For details on how to implement DFEs into your Vuser scripts, see ["How to Implement Data Format Extension \(DFE\) Support" on page 834](#).

## In what situations are DFEs helpful?

When you record a Vuser script, VuGen records the HTTP requests and responses that are passed between the client and the web server. The data in these HTTP requests and responses is often encoded. For example, some of the data may be in binary format. The encoded data may be in the HTTP query string, headers, body, or cookies. When the encoded data is included in a Vuser script, the resulting script will contain data that is difficult to decipher. This makes it difficult to identify text strings that can be used for parameterization and correlation.

The script segment below shows a section of a Vuser script that was generated while recording business processes on a GWT-based application. Notice how some sections of the script contain encoded data and are therefore difficult to decipher.

```
web_custom_request("gwtService",
    "URL=http://lazarus.devlab.ad:8081/GwtComplexObject/org.ega.Main/sampleservice/gwtService",
    "Method=POST",
    "Resource=@",
    "ReqContentType=application/json",
    "Referer=http://lazarus.devlab.ad:8081/GwtComplexObject/",
    "Snapshot=t3.inf",
    "Mode=HTML",
    "EncType=text/x-gwt-rpc; charset=utf-8",
    "Body=6|0|7|http://lazarus.devlab.ad:8081/GwtComplexObject/org.ega.Main/|99EB9620EEB0D48791FBC5BF95BC6300|"
    "|org.ega.client.sampleservice.GWTService"
    "|myMethod|org.ega.client.data.InputData/74817998|LoadRunner|11.52|1|2|3|4|1|5|5|6|7|,
    *AST);
```



LoadRunner uses data format extensions (DFEs) to resolve the difficulties that arise from encoded data in Vuser scripts. DFE support allows easier creation of Vuser scripts by providing the ability to decode the encoded data that is exchanged between the client and the server. By providing the decoded format of the data, the information is presented in the Vuser script in a readable format that enables you to correlate and parameterize the script as required. When the script is replayed, the DFE support re-encodes the modified Vuser script, and enables the Vuser to send the correctly encoded request to the server.


LoadRunner includes a number of pre-defined DFEs. Each DFE is able to decode and encode a specific type of data. For example, the GWT DFE decodes GWT data to XML format when a script is generated, and it encodes XML-formatted data to GWT-formatted data before the script is replayed. For a full list of the pre-defined DFEs, see ["Data Format Extension List" on page 839](#).

When a DFE is applied to a Vuser script and the script is then regenerated, the DFE modifies the script and replaces the encoded data with decoded data. For details on how the script is modified, see ["How DFEs Modify a Vuser Script" on page 838](#).


## When is DFE functionality applied?

You enable DFE support for each Vuser script that requires decoding of encoded data. When DFE support is enabled, the DFE support is applied in the following circumstances:

- Each time the script is generated (after recording) or regenerated. The DFEs are applied to decode the encoded data to produce a script that is easy to decipher.



- Each time the script is run. The DFEs are applied to re-encode the decoded data to produce HTTP messages with encoded data in a format that is expected by the server.



**Note:** In addition to applying DFEs when a script is generated or replayed, it is possible to apply a DFE to a selected string in a Vuser script. For details, see ["Applying DFEs to a String" on page 840](#).

In some scenarios, decoding of encoded data must be performed in a number of stages, until the fully decoded data is produced. Each stage in the conversion process is performed by applying a specified DFE. For example, encoded data from a response may be decoded by applying three

DFEs - first DFE-1, then DFE-2, and then DFE-3. In each stage, the output from one DFE is the input to the next DFE, until the fully decoded data is produced.



## DFE Chains

The series of DFEs that are required to decode encoded data is defined in a **chain**. For example, you could create a chain called **DFE-Chain-1** that includes three DFEs: DFE-1, DFE-2, and DFE-3. The sequence of the DFEs inside a chain is significant - the sequence indicates the order in which the DFEs are applied to the encoded data.



Note that if only a single DFE is required to decode encoded data, the DFE must still be included in a chain.



## Assigning DFE chains

HTTP messages can be divided into a number of sections, including a body, headers, cookies, and a query string. After you define the DFE chains that will be applied to decode and encode a Vuser script, you must specify to which sections of the HTTP messages the DFE chains will apply. Because each HTTP message has only one **Body** section and one **Query String** section, you can specify only a single DFE chain to apply to each of these sections. In contrast, each HTTP message can contain numerous headers and cookies. Consequently, you can specify a particular DFE chain to apply to each header and cookie. For details, see ["How to Apply DFE Chains to Sections of the HTTP Message" on page 837](#).

## Replaying Vuser scripts that contain DFE functionality

When you replay a Vuser script that contains DFE functionality, various messages are added to the Replay log in VuGen's Output pane. Make sure to check these messages to ensure that the DFE functionality is correctly implemented. For further details, see ["Troubleshooting - Data Format Extension \(DFE\)" on page 847](#).


## Custom DFEs

Advanced LoadRunner users can create custom DFEs. For details, see the *HP LoadRunner Data Format Extensions Developer Guide*. In addition, you can use the LoadRunner JavaScript Engine to encode and decode data using common JavaScript libraries. For details, see "[Using the LoadRunner JavaScript Engine](#)" on page 806.

## How to Implement Data Format Extension (DFE) Support

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

In order to implement the DFE support for a Vuser script, you must perform the steps shown in the diagram below:



For additional details about DFEs, see "[Data Format Extensions \(DFEs\) - Overview](#)" on page 831.

## How to Define a Chain of DFEs

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

In order to implement DFE support for a Vuser script, you must first define the DFE chains that are applied by the Vuser. Defining the DFE chains is the first step in implementing DFE support.



Defining the DFE chains includes the following tasks:

### 1. Adding a DFE chain

In VuGen, open the Vuser script.

Click **Record > Recording Options > Data Format Extension > Chain Configuration**.

For details on the dialog box options, see "[Data Format Extension > Chain Configuration Node](#)" on page 191.

Under **Chains**, click the **New Chain** button  and create a new chain. The new chain is listed in the **Chains** pane.

## 2. Adding DFEs to the new DFE chain

In the **Chains** pane, select the chain to which you want to add DFEs.

In the **Chain: <chain name>** pane, click the **Add DFE** button .

In the Add Data Format Extension dialog box, select the DFE that you want to add to the chain, and then click **OK**.

When you add the **GWT** DFE or the **Prefix Postfix** DFE to a chain, you are required to supply additional configuration details about the DFE. For more information, see the documentation about the specific DFE.

For details on the **Chain: <chain name>** pane, see "[Data Format Extension > Chain Configuration Node](#)" on page 191.

After you add a DFE to the chain, select the appropriate option from the **Continue Processing** list. For details on the **Continue Processing** option, see "[Data Format Extension > Chain Configuration Node](#)" on page 191.

Add additional DFEs to the chain as required.

- After defining the required DFE chains, you must enable DFE support for the Vuser script, as described in "[How to Enable DFE Support](#)" below.
- For an overview of the process of implementing DFE support, see "[How to Implement Data Format Extension \(DFE\) Support](#)" on the previous page.
- For additional details about DFEs, see "[Data Format Extensions \(DFEs\) - Overview](#)" on page 831.

## How to Enable DFE Support

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

After you define the DFE chains that are available to a Vuser script, you must enable the DFE support, as described below. Enabling DFE support is the second step in implementing DFE support.



1. In VuGen, open the Vuser script.
2. Click **Record > Recording Options > Data Format Extension > Code Generation**.  
For details on the dialog box options, see "[Data Format Extension > Chain Configuration Node](#)" on page 191.
3. Select the **Enable data format extension** check box.
  - After enabling the DFE support, you can configure the DFE support as described in "[How to Configure DFE Support](#)" below.
  - For details on how to define DFE chains, see "[How to Define a Chain of DFEs](#)" on page 834.
  - For an overview of the process of implementing DFE support, see "[How to Implement Data Format Extension \(DFE\) Support](#)" on page 834.
  - For additional details about DFEs, see "[Data Format Extensions \(DFEs\) - Overview](#)" on page 831.

## **How to Configure DFE Support**

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

After you enable DFE support for a Vuser script, you can configure the DFE support as described below. Configuring DFE support is the third step in implementing DFE support.



1. Open the Vuser script in VuGen.
2. Click **Record > Recording Options > Data Format Extension > Code Generation**.  
For details on the dialog box options, see "[Data Format Extension > Chain Configuration Node](#)" on page 195.
3. Under **Configuration**, from the **Format** list, select the parts of the Vuser script to which the DFEs will be applied.
  - **Code and snapshots**. Applies DFEs to convert the Vuser script code and the snapshot data.

- **Snapshots.** Applies DFEs to convert the snapshot data only - not the Vuser script code.
4. Select the **Verify formatted data** check box to check the results of the data conversion by converting the converted data back to the original state, and then verifying that it matches the original data.
- For details on the dialog box options, see "[Data Format Extension > Code Generation Node](#)" on [page 195](#).
  - After configuring the DFE support, you can assign the DFE chains to specific sections of the HTTP messages. For details, see "[How to Apply DFE Chains to Sections of the HTTP Message](#)" below.
  - For an overview of the process of implementing DFE support, see "[How to Implement Data Format Extension \(DFE\) Support](#)" on [page 834](#).
  - For additional details about DFEs, see "[Data Format Extensions \(DFEs\) - Overview](#)" on [page 831](#).

## ***How to Apply DFE Chains to Sections of the HTTP Message***

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

After you have defined the DFE chains that are available to a Vuser script, enabled and configured DFE support, you must define to which sections of the HTTP messages to apply the DFE chains, as described below. Applying DFE chains to message sections is the last step in implementing DFE support.



1. Open the Vuser script in VuGen.
2. Click **Record > Recording Options > Data Format Extension > Code Generation**.  
For details on the dialog box options, see "[Data Format Extension > Chain Configuration Node](#)" on [page 191](#).
3. [Optional] In the <message section> pane, click **Body** add then select the chain that will be applied to the message body.

4. [Optional] In the <**message section**> pane, click **Headers** add then select the chains that will be applied to the message headers.

**Note:** For VuGen to correctly assign the chain to a specific header, the entry in the **Name** column must be exactly the same as the name of the header in the message.

5. [Optional] In the <**message section**> pane, click **Cookies** add then select the chains that will be applied to the message cookies.

**Note:** For VuGen to correctly assign the chain to a specific cookie, the entry in the **Name** column must be exactly the same as the name of the cookie in the message.

6. [Optional] In the <**message section**> pane, click **Query String** add then select the chain that will be applied to the message query string.

**Note:** Whereas you can modify only the default chain for the **Body** and **Query String** sections, you can add multiple chains for the **Headers** and **Cookies** sections.

- After configuring the DFE support, you can assign the DFE chains to specific sections of the HTTP messages. For details, see "[How to Apply DFE Chains to Sections of the HTTP Message](#)" on the previous page.
- For an overview of the process of implementing DFE support, see "[How to Implement Data Format Extension \(DFE\) Support](#)" on page 834.
- For additional details about DFEs, see "[Data Format Extensions \(DFEs\) - Overview](#)" on page 831.

## How DFEs Modify a Vuser Script

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

When a DFE is applied to a Vuser script and the script is then regenerated, the DFE causes various modifications to be made to the script, as follows:

- VuGen replaces the original encoded text string with a parameter.
- VuGen inserts a **web\_convert\_from\_formatted** function before the function that contains the new parameter. The **web\_convert\_from\_formatted** function contains the decoded value of the original encoded text.

The script section below shows a **web\_custom\_request** function that was generated without DFE support. The **Body** tag in the function includes a text string that is base64 encoded,

**Body=TW9uZGF5.** Because the value of the **Body** tag is encoded, it is difficult to change its value if required for correlation or parameterization purposes.

```
web_custom_request("echo_post.asp",
    "URL=http://example.develab.ad/cgi-bin/temp/echo_post.asp",
    "Method=POST",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t1.inf",
    "Mode=HTTP",
    "Body=TW9uZGF5",
    LAST);
```

After applying Base64 DFE support, the value of the **Body** tag in the regenerated script is replaced with a parameter called **DFE\_PARAM**, "**Body={DFE\_PARAM}**", as shown below.

```
/*TODO: A Correlation scan needs to be performed.*/
web_convert_from_formatted("FormattedData/EscapedBinary=<HP_EXTENSION name=\"Base64\">Monday</HP_EXTENSION>",
    "TargetParam=DFE_PARAM",
    LAST);

web_custom_request("echo_post.asp",
    "URL=http://example.develab.ad/cgi-bin/temp/echo_post.asp",
    "Method=POST",
    "Resource=0",
    "RecContentType=text/html",
    "Referer=",
    "Snapshot=t1.inf",
    "Mode=HTTP",
    "Body={DFE_PARAM}",
    LAST);

return 0;
```

In addition, the modified code also includes a **web\_convert\_from\_formatted** function. The function indicates that the decoded value of the originally encoded string is **Monday**. It is now simple to change the value from **Monday** to any other day by simply changing the decoded value in the **web\_convert\_from\_formatted** function.

## Data Format Extension List

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

The following table lists the pre-defined LoadRunner DFEs (Data Format Extensions). For more information about DFEs, see "[Data Format Extensions \(DFEs\) - Overview](#)" on page 831.

Data Format Extension	Description
Base64 Extension	Decodes strings that are encoded with a Base64 encoder.

Binary to XML Extension	Transforms Microsoft WCF binary XML into XML format.
GWT Extension	Transforms GWT data to XML format.
JSON to XML Extension	Transforms JSON data to XML format.
Prefix Postfix Extension	Enables you to cut data from the beginning and/or end of a string which you do not want decoded. You can add and customize as many prefix/postfix extensions as required. Each postfix/prefix extension created should have a unique display name and tag name.
Remedy to XML Extension	Transforms Remedy request data into XML format. Note that this extension does not transform Remedy response data - which is JavaScript code.
URL Encoding Extension	Decodes strings that are encoded with URL encoding format.
XML Extension	Receives data and checks to see if it conforms with XML syntax. This check allows VuGen to perform correlations based on XPath and to display snapshot data in an XML viewer.
XSS Extension	Enables you to test sites that use Cross Site Scripting (XSS) defense code.

## Applying DFEs to a String

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

You can apply DFEs to a Vuser script to decode encoded data in the script. You can apply the DFEs:

- to specified sections of the Vuser script, when the script is generated or regenerated. For details, see ["How to Implement Data Format Extension \(DFE\) Support" on page 834](#).
- to a single encoded string in the Vuser script, as described in this topic.

For an overview of DFEs, see ["Data Format Extensions \(DFEs\) - Overview" on page 831](#).

**Note:** After you apply a DFE to a string in a Vuser script, VuGen adds an entry to the **Tasks** tab. The added entry indicates that a correlation scan should be performed. For details on

performing a correlation scan, see "Correlation Studio" on page 274.

To apply a DFE to an encoded string in a Vuser script:

1. Open the script in VuGen, and select the encoded text string.
2. Right-click inside the selection, click **Decode with DFE**, and click the name of the chain that contains the DFEs to decode the encoded string. For details on how to define a DFE chain, see "How to Define a Chain of DFEs" on page 834.

VuGen replaces the selected text with a parameter, and adds a **web\_convert\_from\_formatted** function that contains the decoded equivalent of the originally selected text.

**Note:** To change the name that VuGen assigns to new parameters, right-click some encoded text in the Vuser script, click **Decode with DFE > Advanced**, and then specify the parameter name in the **Target Parameter** box. VuGen will add a counter to the parameter name, and increment the counter as required.

## Google Web Toolkit - Data Format Extension (GWT-DFE) - Overview

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

GWT-DFE is one of the standard LoadRunner DFEs. The GWT-DFE support helps to generate Vuser scripts for GWT-based web sites that use the GWT-RPC mechanism. When you record a GWT-RPC based web-site without enabling the GWT-DFE support, the resulting Vuser script may contain significant amounts of data that is cryptic and therefore difficult to decipher, as shown in the code segment below:

```
web_custom_request("gwtservice",
    "URL=http://lazarus.develab.ad:8081/GwtComplexObject/org.ega.Main/sampleservice/gwtservice",
    "Method=POST",
    "Resource=@",
    "RecContentType=application/json",
    "Referer=http://lazarus.develab.ad:8081/GwtComplexObject/",
    "Snapshot=t3.inf",
    "Mode=HTML",
    "EncType=text/x-gwt-rpc; charset=utf-8",
    "Pxy=6|0|7|http://lazarus.develab.ad:8081/GwtComplexObject/org.ega.Main/|99EB9620EEB0D48791FBC5BF95BC6366|"org.ega.client.sampleservice.GWTService"
    "|myMethod|org.ega.client.data.InputData|74817998|LoadRunner|11.52|1|2|3|4|1|5|5|6|7",
    "LAST");
```



The cryptic formatting of the data makes it difficult to identify text strings to be used for correlation, parameterization, and verification.

**Note:** The presence of numerous pipes in the recorded data indicates that the recorded site

may be a GWT-based web site that uses the GWT-RPC mechanism.

When you enable GWT-DFE support, VuGen is able to decode much of the complex data in the HTTP responses and requests. This enables VuGen to generate Vuser scripts that contain data in XML format. In addition, the original coded data contains only values, without the associated names of the data fields. After applying GWT-DFE, the resulting XML-formatted data includes both the names and the values of the data fields. The XML-formatted data in the scripts is therefore easier to decipher, making the scripts easier to correlate, parameterize, and use for verification purposes. The table below shows a sample of code that was generated before and after GWT-DFE support was enabled.

**Example of code generated with and without GWT-DFE support:**

**Original Script - without GWT-DFE Support**

```
6|0|11|http://localhost:8081/MyTestApp/testapp/|624C899BB846618A2E7F49092  
8212946|com.test.client.GreetingService|greetServeCompAns|com.test.client.Com  
plexObject/198661839  
|GWT User|inside object|java.util.HashSet/1594477813|java.lang.String/20040166  
11|add string1|  
string2|1|2|3|4|1|5|5|1001|1999|6|5|321|1234|7|0|8|0|8|2|9|10|9|11|
```

**Script after applying GWT-DFE Support**

```
<HP_EXTENSION name="GWT_DFE_1">
<com.hp.dfe.GWT__Request>
<moduleBaseURL>http://localhost:8081/MyTestApp/testapp/</moduleBaseURL>
<rpcRequest>
<flags>0</flags>
<method>
<class>com.test.client.GreetingService</class>
<name>greetServeCompAns</name>
<parameter-types>
<class>com.test.client.ComplexObject</class>
</parameter-types>
</method>
<parameters>
<com.test.client.ComplexObject>
<anIntField>1001</anIntField>
<anotherIntField>1999</anotherIntField>
<name>GWT User</name>
<objectInComposingField>
<anIntField>321</anIntField>
<anotherIntField>1234</anotherIntField>
<name>inside object</name>
<stringsSet/>
</objectInComposingField>
<stringsSet>
<string>add string2</string>
<string>add string1</string>
</stringsSet>
</com.test.client.ComplexObject>
</parameters>
<serializationPolicy class="com.google.gwt.user.server.rpc.impl.StandardSerializationPolicy"/>
```

### Script after applying GWT-DFE Support

```
</rpcRequest>
</com.hp.dfe.GWT__Request>
</HP_EXTENSION>
```

To enable VuGen to decode the complex data in the HTTP communication, you must identify the .war file that is used by the web application. The .war file contains the logic used by GWT to encode and decode the information in the HTTP communication. VuGen needs access to the .war file so that VuGen can perform similar encoding and decoding procedures. Typically, these .war files are located on the application server, under the web applications folder.

**Note:** Make sure that the .war file that you associate with the Vuser script is the most up-to-date .war file for your application. The .war file is changed each time changes are made to the web application. GWT-DFE support will function correctly only if the most up-to-date .war file is available.

- For an introduction to using DFEs in Vuser scripts, see "[Data Format Extensions \(DFEs\) - Overview](#)" on page 831.
- For details on how to implement DFE support, see "[How to Implement Data Format Extension \(DFE\) Support](#)" on page 834.
- For a full list of the standard LoadRunner DFEs, see "[Data Format Extension List](#)" on page 839.

**Note:** GWT- DFE provides an automatic solution for GWT specific (STRONG\_NAME\_HEADER) correlations.

- **Auto-detection of GWT Remote Procedure Calls (RPCs):**

When VuGen generates or regenerates a Vuser script, VuGen scans the HTTP headers in the requests that are sent to the server. If VuGen detects both a **x-gwt-module-base** text string and a **x-gwt-permutation** text string in any of these HTTP headers, VuGen displays a warning in the VuGen Error tab. The warning recommends that the GWT DFE be enabled for the Vuser script.



**Note:** VuGen will continue to issue the above warning - each time the script is generated or regenerated - until the GWT DFE is enabled.

## Implementing GWT-DFE Support

**Note:** This topic applies to Web (HTTP/HTML) and Silverlight Vuser scripts, and to Web (HTTP/HTML) steps inside Flex Vuser scripts.

This topic provides information that is specific to implementing GWT-DFE support. Use this information in addition to the generic information about implementing DFE support, as described in ["How to Implement Data Format Extension \(DFE\) Support" on page 834](#).

### Prerequisites for implementing GWT-DFE support

LoadRunner includes JRE 1.5. However, many applications are compiled for JVM1.6 and higher. If your application is compiled with JDK1.6 or higher, replace the `<LoadRunner>\jre` folder with `<Program Files>\Java\jre6` before recording a GWT application.

### Recording GWT-DFE Headers

As part of the GWT-DFE support implementation process, it is necessary to specify that VuGen record **x-gwt-permutation** headers when recording business processes. This procedure, as described below, can be performed at any stage of the GWT-DFE support implementation process.

1. Create a script using the Web (HTTP/HTML) protocol.
2. Select **Record > Recording Options > HTTP Properties > Advanced** and then click **Headers**.
3. In the Headers dialog box, select **Record headers in list**.
4. From the **Headers** list, select the **x-gwt-permutation header** check box.

### Applying GWT-DFE chains

When you implement any DFE support, you must apply the DFE chains to specific sections of the HTTP communication. The basic process is described in ["How to Apply DFE Chains to Sections of the HTTP Message" on page 837](#). This topic includes information required when assigning chains while implementing GWT-DFE support. When you assign the chains while implementing GWT-DFE support, you must specify the classpath entries that are associated with the application that is operated by the Vusers. To assign the classpath entries, you must have access to the GWT WAR folder that is used by your development team. The WAR folder includes the following file types:

- \*.gwt.rpc files
- \*.jar files
- \*.class files

### Specifying the classpath entries

1. Select **Record > Recording Options > Data Format Extension > Chain Configuration.**
2. Under **Chains**, click  to create and name a new DFE chain.
3. Click .
4. In the Add Data Format Extension dialog box, select **GWT Extension** and click **OK**.
5. In the **Add GWT to Chain** dialog box, specify the classpath entries:
  - a. If the classpath entries are contained in a single .war file, click  and then specify the location of the .war file.
  - b. If the classpath entries are not contained in a single .war file:
    - Click  to add the folder that contains .gwt.rpc files.
    - Click  to add the application **classes** folder.
    - Click  to add the application **JAR** files from the **WEB-INF\lib** folder.

If the WAR file is extracted on the server, the folder structure will be as follows:

```
<ServerDir>\<applicationDir>\<MyGWTApplication>\<SomeDirContaining  
.gwt.rpc file>
```

WEB-INF\classes

WEB-INF\lib\gwt-servlet.jar

WEB-INF\lib\gwt-servlet-deps.jar

WEB-INF\lib\log4j.jar

WEB-INF\lib\<AdditionalAUTRelatedJarFile>.jar

**Note:** If the location of the classpath entries is not the same on the computer on which the script was recorded and the computer on which the script will be replayed, then

you must modify the run-time settings for the script. Select **Replay > Run-time Settings > Data Format Extension > Chain Configuration** and specify the location of the classpath entries on the computer on which the script will be replayed.

6. Select **Recording Options > Data Format Extension > Code Generation**.
7. Select the **Enable data format extension** check box.
8. Under **Configuration**, select **Code and snapshots** from the **Format** list.
9. Under **Chain Assignment**, select **Body** and assign the chain, select **Headers** and assign the same chain.

## **Troubleshooting - Data Format Extension (DFE)**

This section describes troubleshooting tasks for Vuser scripts that contain DFE functionality.

Replay log: Warning -27040: Data Format Extension: Convert: Empty string returned from extension {Extension name}

When you replay a Vuser script that contains DFE functionality, various messages are added to the Replay log in VuGen's Output pane. The above message indicates that when the Vuser script was replayed, the result of the specified **web\_convert\_from\_formatted** step in the script was an empty string. For some DFEs, returning an empty string from a **web\_convert\_from\_formatted** step is the correct behavior. However, if the Vuser script includes GWT-DFE functionality, the above message may indicate one or both of the following:

- Some of the required classpath files are not included in the run-time settings for the Vuser script.
- Some of the required classpath files do not exist in the specified location on the Load Generator.

For details on how to resolve these issues, see "["Implementing GWT-DFE Support" on page 845](#)".

If you have implemented your own version of DFE, the definition of class **HTTPEntity** in **DfeDefinitions.h** file has been updated in LoadRunner 11.50. No code change is required, but all DFE extensions need be recompiled.

## **Web Services**

### **Web Services - Adding Script Content**

#### **Web Service Testing Overview**

SOA systems are based on Web Services, self-contained applications that can run across the Internet on a variety of platforms. The services are built using Extensible Markup Language (XML)

and Simple Object Access Protocol (SOAP). They serve as building blocks, thereby enabling the rapid development and deployment of new applications.

Using VuGen, you create Vuser scripts for testing your SOA environment. You can use a test generation wizard to automatically generate scripts, or you can create the scripts manually.

## ***Adding Web Service Script Content - Overview***

Web Services scripts let you test your environment by emulating Web Service clients.

After creating an empty Web Services script, as described in "[Create a New Script Dialog Box](#)" on page 170, you add content through one of the following methods: recording, manually inserting Web Service calls, importing SOAP, or by analyzing server traffic.

### **Recording a Web Services Script**

By recording a Web Services session, you capture the events of a typical business process. If you have already built a client that interacts with the Web Service, you can record all of the actions that the client performs. The resulting script emulates the operations of your Web Service client. After recording, you can add more Web Service calls and make other enhancements to the script.

When you record an application, you can record it with or without a Web Service WSDL file. If you include a WSDL file, VuGen allows you to create a script by selecting the desired methods and entering values for their arguments. VuGen creates a descriptive script that can be updated when there are changes in the WSDL.

If you record a script without previously importing a service (not recommended) VuGen creates SOAP requests instead of Web Service call steps. SOAP request arguments are less intuitive and harder to maintain.

For more information, see "[How to Add Content](#)" on page 856.

### **Adding New Web Service Calls**

You can create a Web Services script by manually adding Web Service calls. You design the call based on operation, transport, arguments, and other properties.

For more information, see "[How to Add Content](#)" on page 856.

### **Importing SOAP Requests**

VuGen lets you create Web Service calls from SOAP files. If you have a SOAP request file, you can load it directly into your script. VuGen imports the entire SOAP request (excluding the security headers) with the argument values as they were defined in the XML elements. By importing the SOAP, you do not need to set argument values manually as in standard Web Service calls.

For example, suppose you have a SOAP request with the following elements:

```
- <soap:Body soap:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/">
  - <q1:AddAddr xmlns:q1="http://tempuri.org/AddrBook/message/">
    <Addr href="#id1" />
  </q1:AddAddr>
  - <q2:Addr id="id1" xsi:type="q2:Addr" xmlns:q2="http://tempuri.org/AddrBook/
type/">
    <name xsi:type="xsd:string">Tom Smith</name>
```

```

<street xsi:type="xsd:string">15 Elm Street</street>
<city xsi:type="xsd:string">Phoenix</city>
<state xsi:type="xsd:string">AZ</state>
<zip-code xsi:type="xsd:string">97432</zip-code>
<phone-numbers href="#id2" />
<birthday xsi:type="xsd:date">1983-04-22</birthday>
</q2:Addr>
...

```

When you import the SOAP request, VuGen imports all of the values to the Web Service call. To view the values, in the Step Navigator, right-click the step and then click **Show Arguments**.

To create a new Web Service call based on a SOAP request, you must first import a WSDL file. If a WSDL is not available, or if you want to send the SOAP traffic directly, you can create a SOAP Request step. You specify the URL of the server, the SOAP action, and the response parameter.

In the Editor, the SOAP Request step appears as a **soap\_request** function, described in the Function Reference ([Help > Function Reference](#)).

For more information, see ["How to Add Content" on page 856](#).

## Analyzing Server Traffic

The main focus when testing enterprises and complex systems, is to measure the performance from the client end. Ordinarily, VuGen records the actions you perform in the application or browser, and generates a script emulating the client actions and requests to the server.

In certain test environments, you may be unable to record the client application to retrieve the requests to the server. This may be a result of the server acting as a client, or because you do not have access to the client application. In these cases, you can create a script using VuGen's **Analyze Traffic** feature.

The **Analyze Traffic** feature examines a capture file containing the server network traffic, and creates a script that emulates requests sent to or from the server.

For more information, see ["How to Create a Script by Analyzing Traffic" on page 860](#).

## Script Integration

You can use the completed script to test your system in several ways:

- **Functional Testing.** Run the script to see if your Web services are functional. You can also check to see if the Web service generated the expected values. For more information, see ["Web Services - Preparing Scripts for Replay" on page 878](#).
- **Load Testing.** Integrate the script into a LoadRunner Controller scenario to test the performance of your system under load. For more information, see the *HP Controller* documentation.
- **Production Testing.** Check your Web service's performance over time through a Business Process Monitor configuration. For more information, see the *HP Business Process Monitor* documentation.

## Web Service Call Attachments

When transferring binary files such as images over SOAP, the data must be serialized into XML. Serialization and deserialization can cause a significant amount of overhead. Therefore, it is common to send large binary files using an attachments mechanism. This keeps the binary data intact, reducing the parsing overhead.

Using attachments, the original data is sent outside the SOAP envelope, eliminating the need to serialize the data into XML and making the transfer of the data more efficient.

The formats used for passing a SOAP message together with binary data are MIME (Multipurpose Internet Mail Extensions) and the newer, more efficient DIME (Direct Internet Message Encapsulation) specifications. VuGen supports DIME for all toolkits, but MIME only for the Axis toolkit. To use MIME attachments for the .NET toolkit, see "[User Handler Examples](#)" on page 892.

VuGen supports the sending and receiving of attachments with SOAP messages. You can send Input (Request) or save Output (Response) attachments. For task details, see "[How to Add Content](#)" on page 856.

Output attachments are used to save the response as an attachment. You can choose one of the following options: **Save All Attachments** or **Save Attachment by Index**.

When you specify **Save All Attachments**, VuGen creates three parameters for each attachment based on the parameter name that you specify: a parameter containing the attachment data, the content type of the attachment, and a unique ID for the attachment.

For example, if you specify the name **MyParam** in the **Content** field, the parameter names for the first attachment would be:

```
MyParam_1  
MyParam_1_ContentType  
MyParam_1_ContentID
```

When you specify **Save Attachments by Index**, you specify the index number and name of the parameter in which to store the attachment. The parameter name that you specify for **Content**, is used as a prefix for the Content type and Content ID parameters.

## Special Argument Types

VuGen handles special argument types such as derived, recursive, choice, and optional elements.

### Derived Types

VuGen supports WSDLs with derived types. When setting the properties for a Web Service Call, VuGen allows you to use the base type or derived type for the argument. After you select a type, VuGen updates the argument tree node to reflect the new type. For details, see "[New Web Service Call Dialog Box](#)" on page 865.

### Abstract Types

**Abstract** is a declaration type declared by the programmer. When an element or type is declared to be **abstract**, it cannot be used in an instance document. Instead, a member of the element's substitution group, provided by the XML schema, must appear in the instance document. In such a

case, all instances of that element must use the **xsi:type** to indicate a derived type that is not abstract.

When VuGen encounters an Abstract type, it cannot create an abstract class and replay will fail. In this case, VuGen displays a warning message beneath the **Type** box, instructing you to replace the Abstract type with a derived type.

## Optional Elements

In WSDL files, optional parameters are defined by one of the following attributes:

`minoccurs='0'`

`nillable='true'`

**minoccurs = 0** indicates a truly optional element, that can be omitted. Nillable means that the element can be present without its normal content, provided that the nillable attribute is set to true or 1. By default, the **minoccurs** and **maxoccurs** attributes are set to 1.

In the following example, **name** is mandatory, **age** is optional, and **phone** is nillable.

```
<s:element minOccurs="1" name="name" type="s:string" />
<s:element minOccurs="0" name="age" type="s:int" />
<s:element minOccurs="1" name="phone" nillable="true" type="s:string" />
```

The following table indicates the availability of the options:

Parameter type	Nil radio button	Include arguments in call
Mandatory	disabled	disabled
MinOccurs=0	disabled	enabled
Nillable	enabled	disabled

To include a specific optional argument in the service call, click the node and select **Include Argument in Call**. The nodes for all included arguments are colored in blue. Arguments that are not included are colored in gray.

If you include an element on a parent level, it automatically includes all mandatory and nillable children elements beneath it. If it is a child element, then it automatically includes the parent element and all other mandatory or nillable elements on that level. If you specify **Generate auto-value** to a parent element, VuGen provides values for those child elements that are included beneath the parent.

**Note:** VuGen interprets whether elements are mandatory or optional through the toolkit implementation. This may not always be consistent with the element's attributes in the WSDL file.

## Choice Optional Elements

A Choice element in a WSDL defines a set of elements where only one of them appears in the SOAP message. In some cases, one of the Choice elements is optional, while the others are not. You can select the Choice element and still prevent its optional element from appearing in the


SOAP envelope. In the **Step Navigator**, select the Choice element, and clear the **Include argument in call** option. In Script view, delete the line that defines the Choice argument.

## Recursive Elements

Using the Properties dialog box, you can control the level of recursive elements to include in the Web Service call.

To exclude a certain level and exclude those below, select the lowest parent node that you want to include and select **Include Argument in Call**. VuGen includes the selected nodes, its mandatory children, and all of its parent nodes.

In the following example, three levels of the Choice argument are included—the rest are not. Excluded nodes are grayed out.



## Base 64 Arguments

Base 64 encoding is an encoding method used to represent binary data as ASCII text. Since SOAP envelopes are plain text, you can use this encoding to represent binary data as text within SOAP envelopes.

When VuGen detects a WSDL element of **base64Binary** type, it lets you provide an encoded value. You can specify a value in two ways:

- **Get from file.** Reference a file name.
- **Embed encoded text.** Specify the text to encode.


For details, see "[Process Base64 Data - Simple Data Dialog Box](#)" on page 873.

## Server Traffic Scripts Overview

The main focus when testing enterprises and complex systems, is to measure the performance from the client end. Ordinarily, VuGen records the actions you perform in the application or browser, and generates a script emulating the client actions and requests to the server.

In certain test environments, you may be unable to record the client application to retrieve the requests to the server. This may be a result of the server acting as a client, or because you do not have access to the client application. In these cases, you can create a script using VuGen's **Analyze Traffic** feature.

The **Analyze Traffic** feature examines a capture file containing the server network traffic, and creates a script that emulates requests sent to or from the server. The steps in creating a script by analyzing server traffic are described in "[How to Create a Script by Analyzing Traffic](#)" on page 860.



There are two types of emulations: **Incoming traffic** and **Outgoing traffic**.

**Incoming traffic** scripts emulate situations in which you want to send requests to the server, but you do not have access to the client application, for example, due to security constraints. The most accurate solution in this case is to generate a script from the traffic going **into** the server, from the side of the client.

When you specify an Incoming server network traffic, you indicate the IP address of the server and the port number upon which the application is running. VuGen examines all of the traffic going into the server, extracts the relevant messages, and creates a script. In the above diagram, if the client is unavailable, you could create an Incoming script to emulate the requests coming into **Server A**.

**Outgoing Traffic** scripts emulate the server acting as a client for another server. In an application server that contains several internal servers, you may want to emulate communication between server machines, for example between **Server A** and **Server B** in the above diagram. The solution in this case is to generate a script from the traffic sent as output **from** a particular server.

When you create an Outgoing traffic script, you indicate the IP address of the server whose outgoing traffic you want to emulate, and VuGen extracts the traffic going out of that server. In the

above diagram, an Outgoing script could emulate the requests that **Server A** submits to the **Server B**.

- "Capture Files" below
- "Filtering Traffic" on the next page
- "Data on Secure Servers" on page 856

## Capture Files

A capture file is a trace file containing a log of all TCP traffic over the network. Using a sniffer application, you obtain a dump of all of the network traffic. The sniffer captures all of the events on the network and saves them to a capture file.

To generate a smaller, more manageable script, try to capture the network traffic only for the time that you perform actions in your application.

**Note:** Capture files do not contain loopback network traffic.

You can obtain a capture file using the command line utility or any existing capture tool.

The VuGen command line utility, **Irtcpdump**, is located in the product's **bin** folder. There is a separate utility for each of the platforms: **Irtcpdump.exe** (Windows), **Irtcpdump.hp9**, **Irtcpdump.ibm**, **Irtcpdump.linux**, and **Irtcpdump.solv4**.

### External Capture Tools

Most UNIX operating systems have a built-in version of a capture tool. In addition, there are many downloadable capture tools such as **Ethereal/tcpdump**.

When using external tools, make sure that all packet data is being captured and none of it is being truncated.

Certain capture utilities require additional arguments. For example, **tcpdump** requires the **-s 0** argument in order to capture the packets without truncating their data.

### Troubleshooting Missing Packets

**Issue:** Your script is missing steps you recorded into a capture file.

You encounter the following warning in the **Output Pane > Code generation** tab:

Warning: One or more responses are missing or have missing packets. Therefore, a step may appear to be missing in the script.

This issue can be caused if the recording was stopped before all the responses were received.

If the script is generated from a .pcap file, check if the file has missing packets.

This error may be caused by unnecessary network activity on the recorded machine, which can cause the capturing application to drop packets.

**Steps to Resolve:** Ensure that the capturing machine has no unnecessary network traffic in the background.

**Note:** If you have load on the server that prevents getting responses on time, you can create a script based on requests only by editing the registry.

Go to regedit and add a DWORD key to the below location:

Location:

Software\\Mercury Interactive\\LoadRunner\\Protocols\\HTTP\\Analyzer\\

Key:


AllowAutomaticOutApiEvents = 1

## ***Filtering Traffic***

You can provide a filter to drill down on specific requests going to or from a server, by specifying its IP address and port.

**Tip:** Several external capture tools allow you to filter the IP addresses while capturing the traffic.

You filter the requests by choosing the relevant host IP addresses. The filter can be inclusive or exclusive—you can include only those IPs in the list, or include everything except for those IPs that appear in the list.



For more information, see ["How to Create a Script by Analyzing Traffic" on page 860.](#)

## Data on Secure Servers

To analyze traffic from a secure server, you must provide a certificate containing the private key of the server.

If the traffic is SSL encrypted, you must supply a certificate file and password for decryption. If you want traffic from multiple servers to be reflected in the script, you must supply a separate certificate and password for each IP address that uses SSL.

For more information, see ["How to Create a Script by Analyzing Traffic" on page 860.](#)

## How to Add Content

This topic describes how to add content, such as Web Service calls, to a Web Services Vuser script.

### Prerequisites

Create an empty Web Services Vuser script. Click **File > New Script and Solution** and choose the **Web Services** protocol. You can create either a single-protocol or multi-protocol Vuser script.

## Record a Session - Optional

1. Click the **Start Recording** button  on the VuGen toolbar or press Ctrl+R to open the Recording Wizard > Specify Services screen.

For user interface details, see "[Specify Services Screen](#)" on page 862.

2. Add services to the list. Click **Import** to load a WSDL for the test. Indicate the location of the WSDL file.

For user interface details, see "[Import Service Dialog Box](#)" on page 917.

3. Click **Next**. Specify the location of the application and any other relevant arguments. See the "[Specify Application to Record Dialog Box](#)" on page 863.

## Add a New Service Call - Optional

1. Import a service. Click **Manage Services** to access the Import dialog box.

For user interface details, see "[Import Service Dialog Box](#)" on page 917.

2. Click the cursor at the desired location in your script (**Editor**) or in the test steps (**Step Navigator**).

3. Click the **Add Service Call** button. The New Web Service Call dialog box opens.

4. In the Select Web Service Call section, select a **Service**, **Port Name**, and **Operation**.

5. To specify an endpoint other than the default **Target Address**, select **Override Address** and insert the new endpoint to which you want to submit the requests.

6. Expand the nodes and specify argument values. To create sample values for all Input arguments, select the **Input Arguments** node and click **Generate**. To edit, import, or export the element's XML structure, see "[How to Assign Values to XML Elements](#)" on the next page.

7. To parameterize an input argument, click the node and select the **Value** option. Click the ABC icon and proceed with parameterization. For more information, see "[Parameters](#)" on page 408.

8. Select the **Transport Layer Configuration** node to specify advanced options, such as JMS transport for SOAP messages (Axis toolkit only), asynchronous messaging, or WS Addressing. For more information, see "[How to Send Messages over JMS](#)" on page 895.

## Add Attachments - Optional

1. To add an attachment to an input argument, choose an operation in the left pane. Select **Add to request (Input)**. VuGen prompts you to enter information about the attachment and adds it to the method's tree structure. For details, see the "[Add Input Attachment Dialog Box](#)" on page 872.

2. To specify an output attachment through which to store output arguments, choose an operation in the left pane. Select **Save received (Output)**. Select the desired option: **Save All Attachments** or **Save Attachment by Index** based on their index number—beginning with 1. For details, see "[Web Service Call Attachments](#)" on page 850.
3. To edit the properties of either an Input or Output attachment, click the attachment in the left pane, and enter the required information in the right pane.

## Specify SOAP Headers - Optional

Select the **CustomSOAP Header** node in the left pane and enable the **Use SOAP header** option. You must individually specify SOAP headers for each element. To compose your own, click **Edit** and edit the XML. To import an XML file for the SOAP header, click **Import**.

## Import SOAP - Optional

1. Import a service if one is available. Click **Manage Services** to access the Import dialog box. For more information, see the "[Import Service Dialog Box](#)" on page 917.
2. Click the **Import SOAP** button to open the Import SOAP dialog box.
3. Browse for the XML file that represents your SOAP request.
4. Select the type of step you would like to generate: **Create Web Service Call** or **Create SOAP Request**. In order to create a Web Service Call, you must first import at least one WSDL that describes the operation in the SOAP request file. To view the SOAP before loading it, click **View SOAP**.
5. Click **Load** to import the XML element values.

For a **Web Service Call**, set the properties for the Service call as described in the "[New Web Service Call Dialog Box](#)" on page 865.

For a **SOAP Request**, provide the URL and the other relevant parameters.

6. For a Web Service Call, if there are multiple services with same operation (method) names, select the service whose SOAP traffic you want to import.
7. Click **OK** to generate the new step within your script.

## Analyze Server Traffic - Optional

To create a script by analyzing a file containing a dump of the server traffic, click **Analyze Traffic**.

For details, see "[Server Traffic Scripts Overview](#)" on page 853.

## How to Assign Values to XML Elements

This task describes how to work with XML elements by manually editing the code, importing an external file, and exporting the XML for later use.

## 1. Prerequisites

Import a service and create a new Web Service call. Alternatively, in the Step Navigator, right-click a step and select **Show Arguments**.

## 2. Select the element

In the left pane, select a complex type or array argument. In the right pane, click **XML**. The XML field shows the XML code as a single string.

## 3. Import a file - optional

To import a previously saved XML file, click **Import** and specify the file's location.

## 4. Edit the XML elements - optional

To edit the XML structure and element values, click **Edit**. The XML Editor opens. To import a previously saved XML file, click **Import File**.

- To manually edit the code, click the **Text View** tab.
- To modify the XML through a graphical interface, click the **Step Navigator**. Use the shortcut menu to add children and sibling elements and rename the node. Click **Insert** from the shortcut menu to add a new element before or after the selected one.

## 5. Export a file - optional

To save your XML data to a file so it can be used for other tests, click **Export** and specify a location.

# **How to Generate a Test Automatically**

This task describes how to create requirements or tests for checking your service.

## 1. Open the wizard

Select **File > New** to open the New Virtual User dialog box. Select **SOA Test Generator** in the left pane and click **Create**.

## 2. Add a service

Proceed to the next screen and click **Add** to import at least one service. If your service is not ready yet, you can use an emulated service. For details, see "[How to Add and Manage Services](#)" on page 912. Click **Next**.

## 3. Select testing aspects

Expand the nodes and select the desired testing aspects. Click **Next**.

## 4. Specify a location

Specify a test name and a location for the test scripts: **HP ALM** or a **local file system**. If you

specified ALM, click **Connect** to log on to the server and **Browse** to locate the test node.

## 5. Complete the test generation

Review the summary and include or exclude any scripts from the generation. Click **Generate**.

## 6. Open the scripts

In the final screen, review the list of generated scripts and indicate which ones to open. Click **Finish**.

# **How to Create a Script by Analyzing Traffic**

This task describes how to create a script using a network traffic file.

## 1. Create a capture file on a Windows Platform - optional

Create a capture file containing a log of all TCP traffic over the network on a Windows platform. Use a downloadable capture tool or use the tool provided in the product's **bin** folder, **Irtcpdump.<platform>**. **Note:** You must install WinPcap before using this command. For details, see "[Additional Components](#)" on page 1741.

- a. Run the capture utility in a command window **Irtcpdump -f<file\_name>.cap**. **Irtcpdump** prompts you to select a network card. For Windows, usage is: **Irtcpdump.exe -i interface -f filename** You must provide a file name. If you do not provide an interface, you are prompted to choose one.
- b. Type in the number of the interface card (if there are multiple ones.) and click **Enter**.
- c. Perform typical actions within your application.
- d. Return to the command window and click **Enter** to end the capture session.
- e. Place the capture file on the network in a location accessible to the machine running VuGen.

## 2. Create a capture file on a Linux Platform - optional

Create a capture file containing all TCP traffic over the network on a Linux platform.

- a. Locate the appropriate **Irtcpdump** utility for your platform in the product's **bin** folder. Copy it to a folder that is accessible to your Linux machine. For example, for an HP platform, copy **Irtcpdump.hp9**. If using FTP, make sure to use the binary transfer mode.
- b. Switch to the root user to provide execution permissions: **chmod 755 Irtcpdump.<platform>**
- c. If there are multiple interface cards, **Irtcpdump** uses the first one in alphabetical order. To get a complete list of the interfaces, use the **ifconfig** command.

- d. Run the utility with its complete syntax, specifying the interface and file name. For example, **Irtcpdump.hp9 -ieth0 -f<file\_name>.cap**. The capturing of the network traffic begins.
- e. Perform typical actions within your application.
- f. Return to the window running **Irtcpdump** and follow the instructions on the screen to end the capture session.
- g. Place the capture file on the network in a location accessible to the machine running VuGen.

### 3. Open the Analyzing Traffic wizard

Click the **Analyze Traffic** button or select **Vuser > Analyze Traffic**. For details, see "[Specify Services Screen](#)" on the next page.

### 4. Import a Service - optional

Add one or more services to the list (optional). Click **Import** to load a WSDL file. For details, see the "[Import Service Dialog Box](#)" on page 917.

Click **Next**.

### 5. Specify traffic information

Specify a capture file and the section of the script into which you want to load the traffic: **vuser\_init**, **Action**, or **vuser\_end**.

Indicate whether you want to analyze **Incoming** or **Outgoing** traffic. Specify the server whose traffic you want to analyze.

For details, see "[Specify Application to Record Dialog Box](#)" on page 863.

### 6. Filter the IP addresses - optional

Click the **Filter Options** button to open the Recording options and indicate which IP addresses to ignore or include.

For details, see "[Recording Options](#)" on page 176.

### 7. Configure the SSL - optional

Click the **SSL Configuration** button to add SSL certificates. This is necessary in order to analyze traffic from a secure server.

For details, see the "[SSL Configuration Dialog Box](#)" on page 877.

## How to Create Capture Files Using Irtcpdump

This task describes how to create a capture file using the Irtcpdump utility.

## 1. Install WinPCap

WinPcap allows you to capture network traffic into a file. WinPcap is used in the Server Side Recording feature in the VuGen Web Services protocol. For details, see <http://www.winpcap.org>.

WinPCap can be installed from **LoadRunnerInstallationDVD\Additional Components\WinPcap**.

## 2. Start Irtcpdump.exe

- Open a command line. Drag and drop the Irtcpdump utility to the command line.

The VuGen command line utility, **Irtcpdump**, is located in the **LoadRunnerInstallationDVD\Additional Components\Irtcpdump** folder. There is a separate utility for each of the platforms: **Irtcpdump.exe** (Windows), **Irtcpdump.hp9**, **Irtcpdump.ibm**, **Irtcpdump.linux**, and **Irtcpdump.solv4**.

- Specify the interface (-i) and filename (-f) properties in the command line.

The Interface (-i) property specifies the interface you are using to capture traffic. This property is optional.

**Note:** If you do not define the interface property in the command line, you will be prompted to select one after you press enter.

The Filename (-f) property specifies where (filename and path) to dump the traffic. This property is required.

- Press enter to begin capturing traffic. After you have finished running your business process, return to the command line and press enter to end the capture.

## Specify Services Screen

This dialog box enables specify the basic details needed to begin recording a script.

To access	VuGen > Start Record button
Relevant tasks	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<a href="#">Details...</a>	Opens the Manage Services dialog box for providing further information about the service. For more information, see <a href="#">"Manage Services Dialog Box" on page 913</a> .

<b>Import</b>	Opens the Import Service dialog box. For more information, see the "Import Service Dialog Box" on page 917. For user interface details, see the "Import Service Dialog Box" on page 917.
<b>Delete</b>	Removes the selected service from the list.
<b>&lt;services list&gt;</b>	A list of the available services: <ul style="list-style-type: none"><li>• <b>Service Name.</b> The native name of the service.</li><li>• <b>WSDL Location.</b> The source of the WSDL.</li></ul>

## Specify Application to Record Dialog Box

This dialog box enables specify the basic details needed to begin recording a Web Services script.

<b>To access</b>	VuGen > Start Record button, Next
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Advanced Options....</b>	Opens the Recording Options dialog box. For user interface details, see <a href="#">"Recording Options" on page 176</a> .
<b>Record default Web browser</b>	Records the default browser actions. Specify the starting URL or click the Browse button to navigate to a location.  The Web Services protocol only supports IE as the default browser.
<b>Record any application</b>	Records any Win32 application. You can also specify the following: <ul style="list-style-type: none"><li>• <b>Program to record.</b> Select the browser, internet application, or Win32 application to record</li><li>• <b>Program arguments</b> (Win32 Applications only). Command line arguments for the application. For example, if you specify plus32.exe with the command line options peter@neptune, it connects the user Peter to the server Neptune when starting plus32.exe.</li><li>• <b>Working directory.</b> A working folder for the application (only when required by the application).</li></ul>

**, continued**


<b>Record into action</b>	The section into which you want to record: <b>vuser_init</b> , <b>Action</b> , or <b>vuser_end</b> . For actions you want to repeat, use the <b>Action</b> section. For initialization steps, use <b>vuser_init</b> .
<b>Record application startup</b>	In the following instances, it may not be advisable to record the startup: <ul style="list-style-type: none"> <li>• If you are recording multiple actions, in which case you need to perform the startup in only one action.</li> <li>• In cases where you want to navigate to a specific point in the application before starting to record.</li> <li>• If you are recording into an existing script.</li> </ul>

## Import SOAP Dialog Box

This dialog box enables you to create a test step based on a SOAP file.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"> <li>• Click  Import SOAP</li> <li>• SOA Tools &gt; Import SOAP</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a> <a href="#">"Adding Web Service Script Content - Overview" on page 848</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Browse.</b> Locate the XML file containing SOAP traffic.
	Loads the element values from the SOAP file.
	Opens the Manage Services dialog box for importing and configuring services.
	Opens the SOAP file in a browser for viewing.
<b>&lt;Call type&gt;</b>	The type of call to generate in the script/test: <ul style="list-style-type: none"> <li>• <b>Web Service Call.</b> Requires the import of a service.</li> <li>• <b>SOAP Request.</b> Generates a soap_request step in the script.</li> </ul>

, continued

<b>SOAP Request Properties</b>	The properties of the SOAP request (only visible for <b>SOAP Request</b> type calls). Specify the following:
	<ul style="list-style-type: none"> <li>• <b>URL.</b> The URL or IP address of the server to which to submit the request.</li> <li>• <b>SOAP Action.</b> The SOAP action to include in the request (applicable if there are multiple actions).</li> <li>• <b>Response Parameter.</b> A parameter name to store the response of the SOAP or Web Service call request.</li> </ul>

## New Web Service Call Dialog Box

This dialog box lets you create and configure a new Web Service call.

<b>To access</b>	Open a Web Service Vuser script and then click <b>SOA Tools &gt; Add Service Call</b> or click the <b>Add Service Call</b> button  on the VuGen toolbar.
<b>Important Information</b>	To access the Web Service call properties for existing Web Service calls, select a step in the <b>Step Navigator</b> and choose <b>Properties</b> from the shortcut menu.
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>&lt;service argument tree&gt; (left pane)</b>	An expandable tree hierarchy of the Service containing the following nodes: <ul style="list-style-type: none"> <li>• &lt;operation name&gt;</li> <li>• Transport Layer Configuration</li> <li>• Custom SOAP Header</li> <li>• Input Arguments</li> <li>• Output Arguments</li> </ul>
<b>&lt;parameter values&gt; (right pane)</b>	Enables you to set and select values for each of the left pane's nodes.

, continued

<b>Select Web Service Call</b>	Lets you set the following items: <ul style="list-style-type: none"> <li>• <b>Service.</b> A drop-down list of all of the imported services, with the name derived from the WSDL.</li> <li>• <b>Port Name.</b> A drop-down list of available ports through which to send the request.</li> <li>• <b>Operation.</b> A drop-down list of the service's operations.</li> <li>• <b>Target Address.</b> The default endpoint of the service.</li> <li>• <b>Override Address.</b> Allows you to enter an alternate endpoint address in the <b>Target Address</b> box.</li> </ul>
--------------------------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

### <Operation Name> Node

Allows you to generate sample values for the operation's input arguments and add attachments.

User interface elements are described below:

UI Element	Description
<b>Method</b>	The name of the selected operation (read-only).
<b>Generate auto-values for input arguments</b>	Automatically creates sample values for all of the input arguments, based on their data type.
<b>Attachments</b>	Handles input and output attachments: <ul style="list-style-type: none"> <li>• <b>Add to Request (Input).</b> Attaches a file or parameter value to the request.</li> <li>• <b>Save Received (Output).</b> Saves the response to a parameter.</li> </ul>
<b>Step properties</b>	Lists the following service call properties and their values: <ul style="list-style-type: none"> <li>• WSDL file location</li> <li>• Service name</li> <li>• Port name</li> <li>• Target address</li> <li>• SOAP action</li> <li>• SOAP namespace</li> </ul>

## Transport Layer Configuration Node

User interface elements are described below:

UI Element	Description
<b>HTTP/S Transport</b>	Sets the transport method to HTTP or HTTPS transport.
<b>Async Support</b>	Marks the Web Service call as an asynchronous message activated by an event: <b>Async Event</b> . An arbitrary name for the event. <b>Note:</b> Add a <b>Web Service Wait For Event</b> step to the script, to instruct the replay engine to wait for the event.
<b>WSA Support</b>	Enables WS-Addressing. Use one of the following options for a reply: <ul style="list-style-type: none"> <li>• <b>WS-A Reply</b>. An IP address of the server to reply to when the event occurs.</li> <li>• <b>Autodetect</b>. Reply to the current host when the event occurs. This is useful when running the same script on several machines.</li> </ul> <b>Tip:</b> To use WS-Addressing calls in synchronous mode, leave the <b>Async Event</b> box empty. In Script view, remove the <b>AsyncEvent</b> argument. This instructs the replay to block script execution until the complete response is received from the server.
<b>JMS Transport</b>	Sets the transport method to JMS for <i>synchronous</i> messages. For details, see <a href="#">"Testing Web Service Transport Layers Overview" on page 879</a> . <b>Note:</b> For JMS <i>asynchronous</i> messages, manually add a <b>JMS Send Message Queue</b> or <b>JMS Receive Message Queue</b> step to the script, to set up the message queue information.
<b>Override JMS Queues</b>	Enables you to provide the request and response queues.
<b>Request Queue</b>	The queue name for the request message.
<b>Response Queue</b>	The queue name for the response message.

## Custom SOAP Header Node

Lets you specify additional application-generated header elements to include in the SOAP envelope of an HTTP message. For task details see ["How to Add Content" on page 856](#).

User interface elements are described below:

UI Element	Description
------------	-------------



**, continued**

 Edit...	Opens an XML editor that lets you view and edit the SOAP header XML code.
 Import...	Opens the <b>Select XML File to Import</b> dialog box.
 Export...	Opens the <b>Export SOAP Header into File</b> dialog box.
 REC	Opens the <b>Select or Create New Parameter</b> dialog box.
<b>Use SOAP Header</b>	Includes a SOAP header in the HTTP request.
<b>Header</b>	The header source: <ul style="list-style-type: none"> <li>• For an imported file: Header element as it appears in the imported file.</li> <li>• For a parameter: The parameter name (in curly brackets)</li> </ul>

## **Input Arguments Node**

Lets you set the properties and generate values for all input arguments.





User interface elements are described below:

UI Element	Description
 Include All	Includes all of the method's arguments in the Web Service call.
 Reset	Resets the arguments to their original state. It removes their inclusion in the call, and sets them to the values in the WSDL.
 Generate	Generates sample data for all of the input arguments.
 Edit Argument	Opens the pane for editing the selected argument's value.
<b>Name</b>	The name of the operation (read-only)
<b>Argument List</b>	A list of the input arguments. <ul style="list-style-type: none"> <li>•  Simple parameters</li> <li>•  Arrays (shows the top level only).</li> </ul>

## **<Input Argument Name> Node**

When selecting an input argument, the right pane allows you to specify argument values.

User interface elements are described below:

UI Element	Description
 Add...	Opens the "Add Array Elements Dialog Box" on page 873 for adding a new array element to the input argument (only visible when selecting a parent node in the input array).
 Delete...	Removes the selected array element in the input argument (only visible when selecting a parent node in the input array).
 Include	Includes the sub-arguments of the selected argument, in the Web Service call. This is only enabled for an argument with sub-arguments with the <b>Include argument in call</b> option enabled.
 Exclude...	Excludes the sub-arguments of the parent argument, from the Web Service call.
 Edit...	Opens an XML editor for editing the XML code containing the argument values. The only changes saved are the element values and the number of array elements.
 Import...	Opens the <b>Select XML File to Import</b> dialog box,
 Export...	Opens the <b>Export argument XML into file</b> dialog box.
 REC	Opens the <b>Select or Create Parameter</b> dialog box.
<b>Name</b>	The name of the argument or array.
<b>Include argument in call</b>	Include the argument in the call. For arrays, click <b>Include</b> to add the sub arguments to the call. To exclude all omittable arguments, click <b>Exclude</b> .
<b>Type</b>	The argument type as defined in the WSDL. When the WSDL contains derived types, this box becomes a drop-down list. For details, see " <a href="#">Special Argument Types</a> " on page 850.
<b>Nil</b>	Sets the Nillable attribute to <b>true</b> .
<b>XML (for arrays only)</b>	<ul style="list-style-type: none"> <li>• <b>XML.</b> Enables the <b>Edit</b>, <b>Import</b>, and <b>Export</b> buttons. By editing the XML, you can manually insert argument values. Click on the <b>ABC</b> icon to replace the entire XML structure with a single XML type parameter. <b>Note:</b> This import operation handles XML files that were previously exported—not standard SOAP files.</li> <li>• <b>Generate auto-value for this argument.</b> Inserts automatic values for all children elements.</li> <li>• <b>Add/Delete.</b> Adds or removes elements from the array.</li> </ul>


**, continued**

<b>Value (for non -array elements)</b>	The argument value. To parameterize this value, click the abc icon (only available for non-arrays).
<b>Generate auto-value for this argument</b>	Generates a sample value for the selected argument.

## Output Arguments Node

Lets you see the properties of all output arguments.

User interface elements are described below:

UI Element	Description
	Opens the pane for editing the selected argument's value.
<b>Name</b>	The name of the operation (read-only).
<b>Negative Testing</b>	<p><b>Enables Negative Testing.</b> Confirms that the application did not perform a task that it was not designed to perform. In those cases, you need to verify that the application issued a SOAP Fault, and not a SOAP result response. Select an <b>Expected Response</b>.</p> <ul style="list-style-type: none"> <li>• <b>SOAP Result.</b> A SOAP response to the request.</li> <li>• <b>SOAP Fault.</b> A response indicating that the SOAP request was invalid. Negative Testing applies only to SOAP faults.</li> <li>• <b>HTTP Error.</b> An HTTP error, such as Page Not Found, unrelated to Web Services.</li> </ul> <p>For details, see Negative Testing Overview.</p>
<b>Argument List</b>	A list of the output arguments and the corresponding parameters storing the values.

## <Output Argument Name> Node

Lets you specify a parameter for storing the value of the output argument.

User interface elements are described below:

UI Element	Description

**, continued**

 Add..	Opens the "Add Array Elements Dialog Box" on page 873 for adding a new array element to the output argument (only visible when selecting a parent node in the output array). For details, see the "Add Array Elements Dialog Box" on page 873.
 Delete	Removes the selected array element in the output argument (only visible when selecting a parent node in the output array).
<b>Name</b>	The name of the output argument or array.
<b>Save returned value in parameter</b>	Saves the value of the selected argument to a parameter. To specify a custom parameter name, modify the default Param_<arg_name> in the <b>Parameter</b> field.
<b>Nil</b>	Sets the value of the current argument to <b>nil=true</b> .
<b>XML (for arrays only)</b>	XML code containing the argument values. To parameterize this value, click the abc icon (only available for arrays).

## Output Attachments Node

Lets you set the properties for output attachment parameters. This is only visible if you enabled output attachments in the <Operation Name> Node.

User interface elements are described below:

UI Element	Description
 Add..	Adds a new index-based output argument. This is available only when choosing <b>Save Attachments by Index</b> .
<b>Save All Attachments</b>	Saves all output attachments to a parameter with the following properties: <ul style="list-style-type: none"> <li><b>Content</b>. An editable name for the parameter storing the attachment</li> <li><b>Content-type</b>. The type of parameter (read-only).</li> <li><b>Content-ID</b>. A unique ID for the parameter (read-only).</li> </ul>
<b>Save Attachments by Index</b>	Saves the output attachments to index-based parameters. To set the index, select one of the parameters and modify the index number in the right pane.

## <Output Argument> Node

Lets you set the properties for output attachment parameters. This is only visible if you enabled output attachments in the <Operation Name> Node.

User interface elements are described below:

UI Element	Description
Delete Attachment	Deletes the selected attachment parameter. If you have saved the attachments by index, it only removes the selected item.
Index	An index number for the parameter. This field is only enabled when you select <b>Save Attachments by Index</b> in the <b>Output Attachments Node</b> .
Content	An editable name for the parameter storing the attachment
Content-type	The content type of parameter (read-only).
Content-ID	A unique content ID for the parameter (read-only).

## Add Input Attachment Dialog Box

This page enables you to add input attachments to your Web requests.

To access	Click  Add Service Call and select the top node—the Operation name. Select <b>Add to Request (input)</b> in the <b>Attachments</b> section.
Important information	You must import a service before adding an attachment to a service call. For background information, see " <a href="#">"Web Service Call Attachments" on page 850</a> .
Relevant tasks	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below:

UI Element	Description
Take data from	<p>The location of the data.</p> <ul style="list-style-type: none"> <li>• <b>File.</b> The file location:           <ul style="list-style-type: none"> <li>▪ Absolute Path: The full path of the file. Note that this file must be accessible from all machines running the script.</li> <li>▪ Relative Path: (recommended) A file name. Using this method, during replay, VuGen searches for the attachment file in the script's folder. To add it to the script's folder, select <b>File &gt; Add Files to Script</b> and specify the file name.</li> </ul> </li> <li>• <b>Parameter.</b> The name of a parameter containing the data.</li> </ul>
Content-type	The content type of the file containing the data. The <b>Detect Automatically</b> option instructs VuGen to automatically determine the content type. The <b>Value</b> box accepts manual entries and provides a drop-down list of common content types.
Content-id	A unique identifier for the attachment. By default, VuGen generates this automatically. Optionally, you can specify another ID in the <b>Value</b> box.

## Add Array Elements Dialog Box

This page enables you to add elements to an argument array with an identical structure to the existing array. This is available for both Input and Output arguments.

For Input elements, you can base the new array's values on an existing element.

<b>To access</b>	Click  Add Service Call . Select an argument node that is an array.
<b>Important information</b>	You must have an array in your argument tree in order to view this dialog box.
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below:

UI Element	Description
<b>Name</b>	The name and index of the array's parent node.
<b>Start Index</b>	The index from which to add new array elements.
<b>Elements</b>	The number of identical array elements to add to your argument tree.
<b>Copy values from index</b>	Creates the new array elements with the values of a specific array element (only available for Input arguments).

## Process Base64 Data - Simple Data Dialog Box

This dialog box enables you to set the encoding options for your simple base64 data.

<b>To access</b>	For simple, non-complex Base64 values: <ul style="list-style-type: none"><li>• Select an input argument in the Web Service Call Properties of <b>Base64</b> type.</li><li>• Select the <b>Value</b> option.</li><li>• Choose <b>Embed encoded text</b>.</li><li>• Click the Browse button.</li></ul>
<b>Important information</b>	For a complex array, use the <a href="#">"Process Base64 Data - Complex Data Dialog Box" on the next page</a> .
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below:

UI Element	Description


	Allows you to save the decoded text to a file.
<b>Text to encode</b>	For complex data, use the " <a href="#">Process Base64 Data - Complex Data Dialog Box</a> " below.
<b>Encoding Options</b>	A list of encoding methods. <b>Default:</b> Unicode (UTF-8)
<b>Encoded data</b>	The encoded version of the data from the <b>Text to encode</b> pane.

## Process Base64 Data - Complex Data Dialog Box

This dialog box enables you to set the encoding options for your complex base64 data.

<b>To access</b>	For complex Base64 values: <ul style="list-style-type: none"><li>• Select a complex input argument in the Web Service Call Properties, of <b>Base64</b> type.</li><li>• Select the <b>Value</b> option click the Parameter icon.</li><li>• Replace the value with a parameter.</li><li>• Right-click the Parameter icon in the Value box and select <b>Parameter Properties</b>.</li><li>• Click the <b>Edit Data</b> button.</li><li>• In the desired values set column, click the B64 button.</li></ul>
<b>Important information</b>	For simple, non-complex data, use the " <a href="#">Process Base64 Data - Simple Data Dialog Box</a> " on the previous page.
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below:

UI Element	Description
	Encodes the specified file.
	Enables you to save decoded data to a file. This is usually data obtained during replay.

<b>File</b>	Encode the file by reference or its contents. <ul style="list-style-type: none"> <li><b>File path.</b> The file to encode.</li> <li><b>Link to file.</b> References the file containing the values. If cleared, it uses the content of the specified file. It copies the content to the script folder.</li> </ul> <p><b>Tip.</b> For text exceeding 10KB, enable <b>Link to file</b>.</p>
<b>Text</b>	Encodes the specified text string. <ul style="list-style-type: none"> <li><b>Text to encode.</b> The Base64 text to encode. As you type the text, VuGen encodes it in the <b>Encoded data</b> pane.</li> <li><b>Encoding Options.</b> A list of encoding methods. The default is Unicode (UTF-8).</li> </ul>

## Aspects List

The following table lists the available testing aspects:

Aspect Name	Description
<b>Positive Testing</b>	Generates a full positive test that checks each operation of the service.
<b>Standard Compliance</b>	Checks the service's compliance with industry standards such as WS-I and SOAP.
<b>Service Interoperability</b>	Tests the interoperability of the service's operations with all supported Web Services toolkits. Contains the following sub-aspects: <ul style="list-style-type: none"> <li><b>.NET Framework.</b> Tests that the services are fully interoperable with .NET Framework WSE 2 Toolkit by calling all of its operations with default/expected values.</li> <li><b>Axis/Java Based Web Services.</b> Tests that the services are fully interoperable with Axis 1.3 Web Services Framework by calling all of its operations with default/expected values.</li> </ul>
<b>Security Testing</b>	Tests service security. Contains the following sub-aspects: <ul style="list-style-type: none"> <li><b>SQL Injection Vulnerability.</b> Checks if the service is vulnerable to SQL injections by injecting SQL statements and errors into relevant parameters.</li> <li><b>Cross-site Scripting (XSS).</b> Attempts to hack the service by injecting code into a Web site that will disrupt its functionality.</li> </ul>

, continued

<b>Boundary Testing</b>	Using the negative testing technique, creates tests to manipulate data, types, parameters, and the actual SOAP message to test the service to its limits. Contains the following sub-aspects: <ul style="list-style-type: none"> <li><b>Extreme Values.</b> Provides invalid data types to the services and verifies they are not accepted.</li> <li><b>Null Values.</b> Provides NULL parameters to the services to verify they are not accepted.</li> </ul>
<b>Performance Testing</b>	Contains the following sub-aspects: <ul style="list-style-type: none"> <li><b>Stress Testing.</b> Tests the maximum load that can be placed on the application.</li> <li><b>Overload Sustainability Testing.</b> Tests how well the hardware allocated for the application can support the number of anticipated users.</li> <li><b>Volume Testing.</b> Tests that the system can handle a massive data entry.</li> <li><b>Longevity Test.</b> Tests that the system can sustain a consistent number of concurrent Vusers executing transactions using near-peak capacity, over a minimum 24-hour period.</li> <li><b>Scalability Testing.</b> Repeated stress, overload, volume, and longevity tests with different server or network hardware configurations.</li> </ul>

## Specify Services Screen

This wizard screen enables you to select Web services to associate with your traffic-based script.

<b>To access</b>	Analyze Traffic button
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Opens the <b>Manage Services</b> dialog box for providing further information about the service. For more information, see <a href="#">"Manage Services Dialog Box" on page 913</a> .
	Opens the <b>Import Service</b> dialog box. For more information, see <a href="#">"Import Service Dialog Box" on page 917</a> .
	Removes the selected service from the list.

<b>&lt;services list&gt;</b>	A list of the available services: <ul style="list-style-type: none"><li>• <b>Service Name.</b> The native name of the service.</li><li>• <b>WSDL Location.</b> The source of the WSDL.</li></ul>
------------------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Specify Traffic Information Screen

This wizard screen enables you to specify the capture file for the incoming or outgoing traffic.

<b>To access</b>	<b>Analyze Traffic</b> button, <b>Next</b>
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below:

UI Element	Description
 ...	<b>Browse.</b> Allows you to select a capture file to import.
 Filter Options...	Opens the <b>Traffic Filters</b> node in the Recording Options dialog box. This allows you to specify which IP addresses to include or exclude from the script. For details, see <a href="#">"Recording Options" on page 176</a> .
 SSL Configuration...	Opens the <a href="#">"SSL Configuration Dialog Box" below</a> which allows you to add SSL certificates to analyze traffic from a secure server.
<b>Capture file</b>	The name of a capture file containing the server traffic, usually with a <b>cap</b> extension.
<b>Incoming Traffic</b>	The IP address and port of the server whose incoming traffic you want to examine.
<b>Outgoing Traffic</b>	The IP address of the server whose outgoing traffic you want to examine.
<b>Record into action</b>	The section into which you want to create the script: <b>vuser_init</b> , <b>Action</b> , or <b>vuser_end</b> . For actions you want to repeat, use the <b>Action</b> section. For initialization steps, use <b>vuser_init</b> .

## SSL Configuration Dialog Box

This dialog box enables you to configure the SSL certificate for your traffic file.

<b>To access</b>	<b>Analyze Traffic</b> button, <b>Next</b> ,  SSL Configuration...
<b>Relevant tasks</b>	<a href="#">"How to Add Content" on page 856</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Add Certificate.</b> Adds a new line to the certificate list.
	<b>Delete.</b> Removes the selected certificate.
<certificate list>	<p>The properties of the certificate. Specify the following:</p> <ul style="list-style-type: none"> <li>• <b>IP.</b> IP address of the server being analyzed.</li> <li>• <b>Port.</b> Port of the server being analyzed.</li> <li>• <b>File.</b> The path of the certificate file (with a <b>pem</b> extension) containing the private key. Use the <b>Browse</b> button to locate the file.</li> <li>• <b>Password.</b> A password for decrypting the certificate file.</li> </ul> <p>See <b>Certificate Utility</b> below for details on how to convert certificates.</p>
 <a href="#">Certificate Utility...</a>	<p>Opens the <b>Convert Certificate</b> tab of the <b>SSL Utility</b> that enables you to convert certificates from PKCS #12 and X.509 formats to PEM format.</p> <p>For details on how to convert the certificate to PEM format, see "<a href="#">"SSL Utility" on page 1114</a>, or see <a href="#">Help &gt; LoadRunner Function Reference &gt; Web Vuser Functions (WEB) &gt; Web Vuser Functions &gt; web_set_certificate_ex</a>.</p>

## Web Services - Preparing Scripts for Replay

### Preparing for Replay Overview

After you create a script with Web Service calls, you prepare it for replay.

You can enhance it with custom error and log messages or with transactions. In addition, you can enhance your script with JMS functions, **jms\_<suffix>** or XML functions, **lr\_xml\_<suffix>**. For more information, see the Function Reference ([Help > Function Reference](#)).

Run-time settings let you emulate real users more accurately, configure the run-time settings. These settings include general settings and Web Service specific settings. For details, see "["Run-Time Settings" on page 317](#).

In certain cases, you may need to use the result of one Web Service call as input for another. To do this, you save the result to a parameter and reference it later. For more information, see "["How to Prepare Scripts for Replay" on page 894](#).

## Testing Web Service Transport Layers Overview

Web services can be sent over various transport layers. The transport layer is the protocol used to transport messages to and from the server.

VuGen allows you to configure the transport layer for your services. It fully supports HTTP/HTTPS and JMS (Java Message Service) transport layers.

With user handlers, you can process SOAP requests and responses and assign them a custom behavior. For more information, see "[User Handlers](#)" on page 889.

- ["Sending Messages over HTTP/HTTPS"](#) below

### Sending Messages over HTTP/HTTPS

HTTP is used for sending requests from a Web client, usually a browser, to a Web server. HTTP is also used to return the Web content from the server back to the client.

HTTPS handles secure communication between a client and server. Typically, it handles credit card transactions and other sensitive data.

The typical request and response mechanism is synchronous. In synchronous messaging, the replay engine blocks script execution until the server sends its response. In asynchronous mode, the replay engine executes the script without waiting for server's response for previous messages.

If you are working with HTTP or HTTPS transport, you can use asynchronous calls in conjunction with WS-Addressing. For details, see "["WS-Addressing"](#) on page 882.

### JMS Transport Overview

JMS is a J2EE standard for sending messages, either text or Java objects, between Java clients.

There are two scenarios for communication:

**Peer-to-Peer.** Also known as **Point-to-Point**. JMS implements point-to-point messaging by defining a message queue as the target for a message. Multiple senders send messages to a message queue, and the receiver gets the message from the queue.

**Publish-Subscribe.** Each message is sent from one publisher to many subscribers through a designated topic. The subscribers only receive messages sent after they have subscribed.

VuGen supports point-to-point communication by allowing you to send and receive JMS messages to and from a queue.

Before you can send messages over JMS transport, you need to configure several items that describe the transport:

- **JNDI initial context factory.** The class name of the factory class that creates an initial context which will be used to locate the JMS resources such as JMS connection factory or JMS queue.

- **JNDI provider.** The URL of the service provider which will be used to locate the JMS resources such as JMS connection factory or JMS queue.
- **JMS connection factory.** The JNDI name of the JMS connection factory.

In addition, you can set a timeout for received messages and the number of JMS connections per process.

You configure these settings through the JMS run-time settings. For details, see "["JMS > Advanced Node" on page 366](#)".

This section also includes:

- "["JMS Script Functions"](#) below
- "["JMS Message Structure"](#) on the next page

## ***JMS Script Functions***

VuGen uses its API functions to implement the JMS transport. Each function begins with a **jms** prefix:

Function Name	Description
<b>jms_publish_message_topic</b>	Publishes messages to a specific topic
<b>jms_receive_message_queue</b>	Receives a message from a queue
<b>jms_receive_message_topic</b>	Receives published messages to a specific topic on a subscription.
<b>jms_send_message_queue</b>	Sends a message to a queue.
<b>jms_send_receive_message_queue</b>	Sends a message to a specified queue and receives a message from a specified queue.
<b>jms_subscribe_topic</b>	Creates a subscription for a topic.
<b>jms_set_general_property</b>	Sets a general property in the user context.
<b>jms_set_message_property</b>	Sets a JMS header or property for the next message to be sent, or uses a JMS header or property to filter received messages.

The JMS steps/functions are only available when manually creating scripts—you cannot record JMS messages sent between the client and server.

Unlike peer-to-peer communication that uses message queues, the publish-subscribe functions, **jms\_publish\_message\_topic**, **jms\_subscribe\_topic**, and **jms\_receive\_message\_topic**, are not supported for Web Service calls. To use these functions with Web Service calls, you must manually set up user handlers to generate the JMS message payload. For more information, see ["How to Create a User Handler" on page 900](#).

For details about the JMS functions, see the Function Reference (**Help > Function Reference** or click **F1** on the function).

## **JMS Message Structure**

Each JMS message is composed of:

- **Header.** contains standard attributes (Correlation ID, Priority, Expiration date).
- **Properties.** custom attributes.
- **Body.** text or binary information.

JMS can be sent with several message body formats. Two common formats are **TextMessage** and **BytesMessage**.

To override the default behavior, use a **jms\_set\_general\_property** function before sending the message. Set the **JMS\_MESSAGE\_TYPE** property to **TextMessage**, **BytesMessage**, or **Default**. For Example:

```
jms_set_general_property("step1","JMS_MESSAGE_TYPE","BytesMessage");
```

For more information, see the Function Reference (**Help > Function Reference**).

## **Asynchronous Messages Overview**

You can use VuGen to emulate both synchronous and asynchronous messaging.

In synchronous messaging, the replay engine blocks script execution until the server sends its response. In asynchronous mode, the replay engine executes the script without waiting for server's response for previous messages.

This section also includes:

- ["Sending Asynchronous Calls with HTTP/HTTPS" below](#)
- ["WS-Addressing" on the next page](#)

## **Sending Asynchronous Calls with HTTP/HTTPS**

This following section describes how to use asynchronous calls in HTTP/HTTPS. You use a **Wait for Event** step to instruct Vusers to wait for the response of previous asynchronous requests before continuing. The listener blocks the execution of the service until the server responds.

When adding a Web Service Wait for Event step, you specify the following:

- **Quantifier.** The quantifier indicates whether the Vuser should wait for **ALL** events to receive a response or **ANY**, just one of them. **ANY** returns the name of the first event to receive a response. **ALL** returns one of the event names.
- **Timeout.** the timeout in milliseconds. If no events receive responses in the specified timeout, then **web\_service\_wait\_for\_event** returns a NULL.
- **Events.** a list all of the asynchronous events for which you want to wait.

When running a script with asynchronous messaging, the Replay log provides information about the events and the input and output arguments.

For task details, see "[How to Send Messages over HTTP/S](#)" on page 896.

When setting up an asynchronous message, you can set the location to which the service responds when it detects an event using WS-Addressing. For more information, see "[WS-Addressing](#)" below.

## **WS-Addressing**

WS-Addressing is a specification that allows Web Services to communicate addressing information. It does this by identifying Web service endpoints in order to secure end-to-end endpoint identification in messages. This allows you to transmit messages through networks that have additional processing nodes such as endpoint managers, firewalls, and gateways. WS-Addressing supports Web Services messages traveling over both synchronous or asynchronous transports.

The WS-Addressing specification requires a **WSAReplyTo** address—the location to which you want the service to reply.

An optional **WSAACTION** argument allows you to define a SOAP action for instances where transport layers fails to send a message.

The following example illustrates a typical SOAP message using WS-Addressing, implemented in the background by VuGen.

```
<S:Envelope xmlns:S="http://www.w3.org/2003/05/soap-envelope"
             xmlns:wsa="http://www.w3.org/2004/12/addressing">
  <S:Header>
    <wsa:MessageID>
      http://example.com/SomeUniqueMessageIdString
    </wsa:MessageID>
    <wsa:ReplyTo>
      <wsa:Address>http://myClient.example/someClientUser</wsa:Address>
    </wsa:ReplyTo>
    <wsa:Address>http://myserver.example/DemoErrorHandler</wsa:Address>
    </wsa:FaultTo>
    <wsa:To>http://myserver.example/DemoServiceURI</wsa:To>
    <wsa:Action>http://myserver.example/DoAction</wsa:Action>
  </S:Header>
  <S:Body>
    <!-- Body of SOAP request message -->
```

```
</S:Body>
</S:Envelope>
```

In the following example, the server responds to the interface 212.199.95.138 when it detects Event\_1.

```
web_service_call("StepName=Add_101",
    "SOAPMethod=Calc.CalcSoap.Add",
    "ResponseParam=response",
    "AsyncEvent=Event_1",                      "WSAReplyTo=212.199.95.138",
    "WSDL=http://lab1/WebServices/CalcWS/Calc.asmx?wsdl",
    "UseWSDLCopy=1",
    "Snapshot=t1153825715.inf",
    BEGIN_ARGUMENTS,
        "first=1",
        "second=2",
    END_ARGUMENTS,
    BEGIN_RESULT,
        "AddResult=Param_AddResult1",
    END_RESULT,
    LAST);
```

You can issue WS-Addressing calls in both asynchronous and synchronous modes. To use WS-Addressing in synchronous mode, leave the **Async Event** box empty in the Transport Layer options. In Script view, remove the **AsyncEvent** argument. This instructs the replay engine to block script execution until the complete response is received from the server.

For task details, see ["How to Send Messages over HTTP/S" on page 896](#).

## **Database Integration Overview**

When testing your Web Service, it is vital that you use data that is accurate and up to date. If you use a snapshot of data from a past date, it may no longer be valid or relevant.

The database integration allows you to access values in a database during your test, ensuring that the data is up to date.

The database integration functions are useful in the following scenarios:

- ["Connecting to a Database" on the next page](#)
- ["Using Data Retrieved from SQL Queries" on the next page](#)
- ["Validating Database Values after a Web Service Call" on page 886](#)
- ["Checking Returned Values Through a Database" on page 887](#)
- ["Performing Actions on Datasets" on page 889](#)

## Connecting to a Database

To connect to a database, you add a connection step to your script. A built-in Connection String Generator guides you in creating a database connection string specific to your database and credentials. You can also test your connection before inserting the step.

When running your script with iterations, virtual users only repeat the **Action** section of the script. If you include the database connection step in the **Action** section, the test will repeat it for each iteration. Virtual Users only repeat the **Action** section of the script, but not the **vuser\_init** or **vuser\_end** sections. Therefore, we recommend that you place the database connection step in the **vuser\_init** section, and the disconnect step, **lr\_db\_disconnect** in the **vuser\_end** section.

In cases where you only need to do one query and scroll through the data, you should also place the **Database: ExecuteSQL Query** step in the **vuser\_init** section.

For task details, see "[How to Send Messages over JMS](#)" on page 895.

## Using Data Retrieved from SQL Queries

In this scenario, the test fetches data from the database and uses it at a later point in the script, such as calls to the Web Service. Since the script retrieves the data during each test run, the data is up to date and relevant.

The following table shows a typical flow of the script:

Step	API function
Connect to database	lr_db_connect
Execute an SQL query	lr_db_executeSQLStatement
Retrieve and save the data	lr_db_getvalue to <param_name>
Web Service call	web_service_call with {<param_name>}
Disconnect from database	lr_db_disconnect

You can iterate through the results in two ways:

- save them to a simple parameter during each iteration
- use VuGen built-in iterations to scroll through the data

For more information, see the Function Reference ([Help > Function Reference](#)).

In the following example, the **vuser\_init** section connects to the database and performs a database query.

```
vuser_init()
{
    lr_db_connect("StepName=myStep",

```

```

    "ConnectionString=Initial Catalog=MyDB;Data Source=mylab.net;user id =sa ;pa
    ssword = 12345;" ,
    "ConnectionName=MyConnection",
    "ConnectionType=SQL",
    LAST);
lr_db_executeSQLStatement("StepName=MyStep",
    "ConnectionName=MyConnection",
    "SQLQuery=SELECT * FROM Addresses",
    "DatasetName=ds1",
    LAST);
return 0;
}

```

At the end of your test, disconnect from the database in the **vuser\_end** section.

```

vuser_end()
{
    lr_db_connect("StepName=myStep",
        "ConnectionString=Initial Catalog=MyDB;Data Source=LAB1.devlab.net;user
        id =sa ;password = soarnd1314;" ,
        "ConnectionName=MyConnection",
        "ConnectionType=SQL",
        LAST);
    return 0;
}

```

In the Action section, you include the steps to repeat. Note the use of the **Row** argument. In the first call to the database, you specify the first row with **Row=next**. To retrieve another value in the same row, use **current**.

```

Action()
{
    lr_db_getvalue("StepName=MyStep",
        "DatasetName=ds1",
        "Column=Name",
        "Row=next",
        "OutParam=nameParam",
        LAST);
    lr_db_getvalue("StepName=MyStep",
        "DatasetName=ds1",
        "Column=city",
        "Row=current",
        "OutParam=cityParam",
        LAST);
/* Use the values that you retrieved from the database in your Web Service call
*/
    web_service_call( "StepName=EchoAddr_101",
        "SOAPMethod=SanityService|SanityServiceSoap|EchoAddr",
        "ResponseParam=response",
        "Service=SanityService",
        "ExpectedResponse=SoapResult",

```

```

"Snapshot=t1227168459.inf",
BEGIN_ARGUMENTS,
"xml:addr="
    "<addr>"
        "<name>{nameParam}</name>"
        "<street></street>"
        "<city>{cityParam}</city>"
        "<state></state>"
        "<zip></zip>"
    "</addr>",
END_ARGUMENTS,
BEGIN_RESULT,
END_RESULT,
LAST);
return 0;
}

```

## **Validating Database Values after a Web Service Call**

In this scenario, the test executes a Web Service call that modifies a database on the backend. The goal of this scenario is to validate that the resulting values in the database are correct.

The following table shows a typical flow of the script:

Step	API function
Connect to database	lr_db_connect (in <b>vuser_init</b> section)
Web Service call	web_service_call
Execute an SQL query	lr_db_executeSQLStatement
Retrieve and save the data	lr_db_getvalue to <param_name>
Check the data	lr_checkpoint
Disconnect from database	lr_db_disconnect (in <b>vuser_end</b> section)

For more information, see the Function Reference ([Help > Function Reference](#)).

The following example illustrates this process of checking the data:

```

Action()
{
/* A Web Service call that modifies a database on the back end. */
    web_service_call( "StepName=addAddr_102",
                      "SOAPMethod=Axis2AddrBookService|Axis2AddrBookPort|addAddr",
                      "ResponseParam=response",
                      "Service=Axis2AddrBookService",
                      "ExpectedResponse=SoapResult",
                      "Snapshot=t1227169681.inf",

```

```

BEGIN_ARGUMENTS,
"xml:arg0="
"<arg0>"
    "<name>{Customers}</name>"
    "<city>{City}</city>"
    "</arg0>",
END_ARGUMENTS,
LAST);
/* Query the database by the cusotmer name that was modified by the Web Service */
1r_db_executeSQLStatement("StepName=MyStep",
    "ConnectionName=MyConnection",
    "SQLQuery=SELECT * FROM Addresses WHERE name = '{Customers}' ",
    "DatasetName=ds1",
    LAST);
/* Get the values retrieved by the database query. */
1r_db_getvalue("StepName=MyStep",
    "DatasetName=ds1",
    "Column=Name",
    "Row=current",
    "OutParam=CustomerName",
    LAST);
/* Compare the actual value with the expected value stored in the database. */
1r_checkpoint("StepName=validateCustomer",
    "ActualValue={Customers}",
    "ExpectedValue={CustomerName}",
    "Compare=Equals",
    "StopOnValidationError=false",
    LAST);
return 0;
}

```

## ***Checking Returned Values Through a Database***

In this scenario, the user executes a Web Service call which returns an XML response. The goal of this scenario is to validate the response of the Web Service call against expected values. The expected values are stored in a database. The script fetches the expected results from a database and then compares them with the actual response.

The following table shows a typical flow of the script:

Step	API function
Connect to database	lr_db_connect (in <b>vuser_init</b> section)
Web Service call	web_service_call with <b>Result=&lt;result_param&gt;</b>
Execute an SQL query	lr_db_executeSQLStatement

Retrieve the expected data	<code>lr_db_getvalue</code> to <param_name>
Validate the data	<code>soa_xml_validate</code> with an XPATH checkpoints.
Disconnect from database	<code>lr_db_disconnect</code> (in <b>vuser_end</b> section)

You can use the XML validation tool to create a checkpoint for the response data. When creating the validation step, use the database parameter that you retrieved through `lr_db_getvalue`.

The following example illustrates a typical validation of data returned by a Web Service call. The Validation step compares the actual expected results:

```
Action()
{
    web_service_call( "StepName=GetAddr_102",
        "SOAPMethod=AddrBook|AddrBookSoapPort|GetAddr",
        "ResponseParam=response",
        "Service=AddrBook",
        "ExpectedResponse=SoapResult",
        "Snapshot=t1227172583.inf",
        BEGIN_ARGUMENTS,
        "Name=abcde",
        END_ARGUMENTS,
        BEGIN_RESULT,
        END_RESULT,
        LAST);
    lr_db_executeSQLStatement("StepName=MyStep",
        "ConnectionName=MyConnection",
        "SQLQuery=SELECT * FROM Addresses WHERE name = 'abcde' ",
        "DatasetName=ds1",
        LAST);
    lr_db_getvalue("StepName=MyStep",
        "DatasetName=ds1",
        "Column=Name",
        "Row=current",
        "OutParam=CustomerName",
        LAST);
    soa_xml_validate ("StepName=Xm1Validation_1146894916",
        "Snapshot=t623713af7a594db2b5fef43da68ad59d.inf",
        "XML={GetAddrAllArgsParam}",
        "StopOnValidationError=0",
        BEGIN_CHECKPOINTS,
        CHECKPOINT,"XPATH=/*[local-name(.)='GetAddr'][1]/*[local-name(.)='Re
sult'][1]/*[local-name(.)='name'][1]","Value_Equals={CustomerName}",
        END_CHECKPOINTS,
        LAST);
    return 0;
}
```

For more information, see the Function Reference ([Help > Function Reference](#)).

## Performing Actions on Datasets

VuGen lets you perform actions on datasets returned by SQL queries.

The **lr\_db\_dataset\_action** function performs the following actions on datasets:

- **Reset.** Set the cursor to the first record of the dataset.
- **Remove.** Releases the memory allocated for the dataset.
- **Print.** Prints the contents of the entire dataset to the Replay Log and other test report summaries.

Note that when you retrieve binary data through **lr\_db\_getvalue**, you cannot print its contents using the **Print** action.

For information about the syntax and usage of this function, see the Function Reference (**Help > Function Reference**).

## Customizing Overview

VuGen provides several advanced capabilities that allow you to customize the way your script behaves. These capabilities are user handlers and configuration files.

With user handlers, you can process SOAP requests and responses and assign them a custom behavior. For more information, see below.

Configuration files let you customize advanced settings such as security information and the WSE configuration.

- "[User Handlers](#)" below
- "[Custom Configuration Files](#)" on page 891

## User Handlers

User Handlers are open APIs through which you can perform the following operations:

- Get and set the request/response SOAP envelopes
- Override the transport layer
- Get and set the request/response content type
- Get and Set values for LoadRunner parameters

- Retrieve a configuration argument from the script
- Issue messages to the execution log
- Fail an execution

You can set up a user handler directly in a script, or implement it through a DLL. You can apply the handler locally or globally.

For task details, see "[How to Create a User Handler](#)" on page 900.

For sample user handlers, see "[User Handler Examples](#)" on page 892.

## Handler Function Definitions

For basic implementation of a user handler, you define a user handler function within your Vuser script with the following syntax:

```
int MyScriptFunction(const char* pArgs, int isRequest)
```

The **pArgs** argument contains the string that is specified in **UserHandlerArgs** argument of **web\_service\_call** function.

The **isRequest** argument indicates whether the function is being called during processing of a Request (1) or Response (0) SOAP envelope.

The content of SOAP envelope is passed to a parameter called **SoapEnvelopeParam** for both requests and responses. After the function processes the SOAP envelope, make sure to store it in the same parameter.

To call the handler function, use the function name as a value for the **UserHandlerFunction** argument in the relevant Web Service Call step. For more information, see the Function Reference ([Help > Function Reference](#)).

## Event Handler Return Codes

VuGen recognizes the following return codes for the handler function.

Return Code	Description
LR_HANDLER_SUCCEEDED	0 The Handler succeeded, but the SOAP envelope did not change.
LR_HANDLER_FAILED	1 The Handler failed and further processing should be stopped.
LR_HANDLER_SUCCEEDED_AND_MODIFIED	2 The Handler succeeded and the updated SOAP envelope is stored in <b>SoapEnvelopeParam</b> .

In the following example, a script handler manipulates the outgoing envelope:

```
//This function processes the SOAP envelope before sending it to the server.
int MyScriptFunction(const char* pArgs, int isRequest)
{
```

```

if (isRequest == 1) {
    //Get the request that is going to be sent
    char* str = lr_eval_string("{SoapEnvelopeParam}");
    //Manipulate the string...
    //Assign the new request content
    lr_save_string(str, "SoapEnvelopeParam");
    return LR_HANDLER_SUCCEEDED_AND_MODIFIED;
}
return LR_HANDLER_SUCCEEDED;
}
Action()
{
    //Instruct the web_service_call to use the handler
    web_service_call( "StepName=EchoAddr_102",
        "SOAPMethod=SpecialCases.SpecialCasesSoap.EchoAddr",
        "ResponseParam=response",
        "userHandlerFunction=MyScriptFunction",
        "Service=SpecialCases",
        "Snapshot=t1174304648.inf",
        BEGIN_ARGUMENTS,
        "xml:addr="
            "<addr>"
                "<name>abcde</name>"
                "<street>abcde</street>"
                "<city>abcde</city>"
                "<state>abcde</state>"
                "<zip>abcde</zip>"
            "</addr>",
        END_ARGUMENTS,
        BEGIN_RESULT,
        END_RESULT,
        LAST);
    return 0;
}

```

## **Custom Configuration Files**

Configuration files let you customize advanced settings such as security information and the WSE configuration. These files let you control the behavior of the test during run time.

The standard .NET configuration file, **mmdrv.exe.config**, is located in the VuGen installation folder. Some applications have their own configuration file, **app.config**.

You can customize the test run further, by filtering out the input or output. In addition, you can configure security information, such as token information and whether or not to allow unsigned test certificates.

For task details, see "[How to Customize Configuration Files](#)" on page 903.

## User Handler Examples

This section illustrates several common uses for user handlers.

### .NET Filters

You can apply a .NET filter to your messages using the user handler mechanism.

If you are familiar with Microsoft's Web Service Enhancements (WSE) 2.0, you can create a .NET filter and register it for incoming or outgoing SOAP messages. A .NET filter is a class that is derived from Microsoft.Web.Services2.SoapInputFilter or Microsoft.Web.Services2.SoapOutputFilter. By overriding the **ProcessMessage** function of this class, you can examine and modify the envelope's body and header.

To define the filter globally for the entire script, add the following lines to the script's default.cfg file below.

```
[UserHandler]
Function=LrWsSoapFilterLoader
Args=<Filters InputFilterClass="class name" InputFilterLib="lib name" OutputFilterClass="class name" OutputFilterLib="lib name" />
Order=BeforeSecurity/AfterSecurity/AfterAttachments
```

The **InputFilterClass** parameter indicates the name of your class, and **InputFilterLib** indicates the name of the assembly in which the class resides. For example:

```
web_service_call(
    ...
    "UserHandlerName=LrWsSoapFilterLoader",
    "UserHandlerArgs=<Filters InputFilterClass=\"MyFilterNamespace.MyFilterClassName\" InputFilterLib=\"MyAssemblyName\" />",
    BEGIN_ARGUMENTS,
    ...
    END_ARGUMENTS,
    ...
);
```

Use SoapOutputFilter to examine an outgoing **web\_service\_call** request, and SoapInputFilter to examine the response from the server. Use **InputFilterClass** and **InputFilterLib** if your filter is derived from SoapInputFilter, or **OutputFilterClass** and **OutputFilterLib** if your filter is derived from SoapOutputFilter.

To define the filter for a specific step, add the following arguments to the **web\_service\_call** function.

```
UserHandlerName= LrWsSoapFilterLoader
UserHandlerArgs=<Filters InputFilterClass=\"class name\" InputFilterLib=\"lib name\" OutputFilterClass=\"class name\" OutputFilterLib=\"lib name\" />
UserHandlerOrder=BeforeSecurity/AfterSecurity/AfterAttachments
```

### Overriding the Transport Layer

The following example shows a user handler function overriding the transport layer. VuGen does not

automatically send the SOAP request over HTTP transport—instead it follows the transport method indicated in the custom handler.

After you receive a response, set the response envelope with the command:

```
lr_save_string(someResponseEnvelopeStr, "SoapEnvelopeParam");
```

To apply an alternate transport layer, specify **ReplaceTransport** as a value for the **UserHandlerOrder** argument. Define the transport layer in the handler.

```
web_service_call(
    ...
    "UserHandlerFunction=<Transport HandlerFunction>",
    "UserHandlerArgs=<handler arguments>",
    "UserHandlerOrder=ReplaceTransport"
    ...
LAST);
```

## Including MIME Attachments

When working with Web Service scripts based on the .NET toolkit, the infrastructure does not support MIME attachments. Using the handlers mechanism, you can add MIME attachment functionality to .NET scripts.

The following sections describe how to send and receive MIME attachments for the .NET toolkit. You can receive and send a MIME attachment in the same operation.

## Sending MIME Attachments

To send a MIME attachment, add the boldfaced code to the **web\_service\_call**:

```
web_service_call( "StepName=EchoComplex_101",
    "SOAPMethod=SimpleService|SimpleServiceSoap|EchoComplex",
    "ResponseParam=response",
    "Service=SimpleService",
    "UserHandlerName=LrWsAttachmentsHandler", "UserHandlerArgs=ATTACHMENT_ADD; AT
TACHMENTS_FORMAT_MIME; ContentType=text/plain; FileName=C:\\temp\\results.disc
omap",
    "ExpectedResponse=SoapResult",
    "Snapshot=t1208947811.inf",
    BEGIN_ARGUMENTS,
    "xml:cls=",
    "<cls>"
    "<i>123456789</i>"
    "<s>abcde</s>"
    "</cls>",
    END_ARGUMENTS,
    BEGIN_RESULT,
    END_RESULT,
    LAST);
```

Modify the **FileName** and **ContentType** parameters to indicate the actual path and content type.

## Receiving MIME Attachments

To receive a MIME attachment, add the following code to the **web\_service\_call**:

```
"UserHandlerName=LrWsAttachmentsHandler",
"UserHandlerArgs=ATTACHMENT_SAVE_ALL;ParamNamePrefix=attach;"
```

## Sending and Receiving MIME Attachments

To send and receive a MIME attachment in the same **web\_service\_call**, modify the Web Service call as shown below:

```
"UserHandlerName=LrWsAttachmentsHandler",
"UserHandlerArgs=ATTACHMENT_SAVE_ALL;ParamNamePrefix=attach; ATTACHMENT_ADD; ATTACHMENTS_FORMAT_MIME; ContentType=text/plain; FileName=C:\\temp\\results.discomap",
```

# **How to Prepare Scripts for Replay**

This task describes how to prepare the script for replay and run it.

## Assign Input Parameter Values

First save the output result to a parameter, and then reference that parameter in a later Web Service call.

1. **Save the output parameter.**
  - a. In the **Step Navigator**, double-click the Web Service call whose output you want to use, to view its properties.
  - b. In the left pane, select the output argument whose value you want to save to a parameter.
  - c. In the right pane, select **Save returned value in parameter**. Specify a name in the **Parameter** box.
2. **Use the saved parameter for input.**
  - a. In the **Step Navigator**, double-click the Web Service call whose input parameters you want to set.
  - b. In the left pane, select the input argument for which to use the saved parameter.
  - c. In the right pane, select **Value**, and click on the abc icon. The Select or Create Parameter box opens.
  - d. Select the saved output parameter from the **Parameter name** list.
  - e. To specify an input parameter in Script view, select the value you want to replace and select **Use Existing Parameters** from the shortcut menu. Select one of the available parameters.

## Set the Run-time Setting - Optional

Open the run-time settings (F4) to configure JMS and VM settings. Click the **JMS > Advanced** node. For user interface details, see the "[JMS > Advanced Node](#)" on page 366.

## Configure XSDs With any type Elements - Optional

For Web Services that have an XSD schema with an **Any** type element, `<xsd:element name="<Any_element>" type="xsd:anyType" />`, check that the script conforms with the following model:

```
BEGIN_ARGUMENTS,
    "xml:Any_element="
        "<Any_element>"
        "<string>the string to send</string>"
        "</Any_element>",
END_ARGUMENTS,
```

The actual SOAP may differ slightly, but as long as your script conforms to the above model, it will run properly.

You can also send complex type elements for the **<any>** type. For example:

```
"xml:Any_element="
    "<Any_element>"
    "<myComplexTypeName>"
    "<property1>123</property1>"
    "<property2>456</property2>"
    "</myComplexTypeName>"
    "</Any_element>,
```

## Run the Script

Click **Replay > Run**. Observe the output log for relevant messages.

### Review the Test Results

The Test Results viewer opens automatically after the test run. An X indicates a failed step.

Expand the nodes to see detailed information about the SOAP response and checkpoints. For details, see "[Viewing Replay Results](#)" on page 479.

## How to Send Messages over JMS

This task describes how to send messages using the JMS transport method.

### 1. Open the step properties

In the **Step Navigator**, select the step whose transport you want to set, and then select **Show Arguments** from the shortcut menu.

### 2. Select the JMS transport method

Select the **Transport Layer Configuration** node and choose **JMS Transport**.

For UI details, see "[New Web Service Call Dialog Box](#)" on page 865.

### 3. Set the run-time settings - optional

Configure the run-time settings. For details, see "[JMS > Advanced Node](#)" on page 366.

### 4. Send synchronous JMS messages - optional

Once you create a Web Service call and designate the transport method as JMS, VuGen sends the JMS messages in a synchronous manner. If desired, specify the queue information.

### 5. Send asynchronous JMS messages - optional

To implement asynchronous messages over JMS, you send the request or retrieve the response using JMS steps—not Web Service calls.

- a. Click within the script at the desired location. Select **Insert > New Step** and expand the **JMS Functions** node.
- b. Select a JMS function: **JMS Send Message Queue** sends a message to a queue. **JMS Receive Message Queue** receives a message from the queue.
- c. Click **OK** to open the JMS function properties.
- d. Specify a queue name and click **OK** to generate the JMS functions.

For additional information about these functions, see the Function Reference (**Help > Function Reference** or click **F1** on the function).

### 6. Send messages over JMS using SOAP messages - optional

To send messages over JMS, using the SOAP message and without a Web Service call:

- a. Record SOAP messages using a standard Web protocol.
- b. Click within the script at the desired location. Select **Insert > New Step** and expand the **JMS Functions** node.
- c. Select a JMS function: **Send Message Queue** or **JMS Receive Message Queue**.
- d. Click **OK** to open the JMS function properties.
- e. Specify a queue name and click **OK** to generate the JMS functions.

For details, see the Function Reference (**Help > Function Reference** or click **F1** on the function).

## How to Send Messages over HTTP/S

This task describes how to send messages using the HTTP transport method.

- 1. Open the step properties**

In the **Step Navigator**, select the step whose transport you want to set, and then select **Show Arguments** from the shortcut menu.

- 2. Select the HTTP/S transport method**

Select the **Transport Layer Configuration** node and choose **HTTP/S Transport**.

- 3. Send a HTTP synchronous message - optional**

To send messages in synchronous mode over HTTP, create a standard Web Service call, and do not enable the **Async Support** option.

- 4. Send asynchronous HTTP messages - optional**

- a. Choose **HTTP/S Transport** and select the **Async Support** option.
- b. Type an event name in the **Async Event** box.
- c. Click **OK** to generate the Web Service call.
- d. Add a **Wait for Event** step. Select **Insert > New Step** and choose **Web Service Wait for Event**.
- e. Specify a step name, a quantifier, and a timeout. Click **Add** and insert the name of the event that you defined in the previous step.

In Script view, VuGen indicates asynchronous messaging with the added parameter, **AsyncEvent**.

```
web_service_call("StepName=EchoString_101",
    "SOAPMethod=EchoRpcEncoded.EchoSoap.EchoString",
    "ResponseParam=response1",
    "Service=ExtendedECHO_rpc_encoded",
    "AsyncEvent=Event_1",
    "Snapshot=t1157371707.inf",
    BEGIN_ARGUMENTS,
    "sec=7",
    "strString=mytext",
    END_ARGUMENTS,
    BEGIN_RESULT,
    "EchoStringResult=first_call",
    END_RESULT,
    LAST);
```

The **AsyncEvent** flag instructs the Vuser to wait for the response of previous asynchronous service requests.

- 5. Send an asynchronous message using WS-Addressing - optional**

- a. Select the **Async Support** option and provide an event name in the **Async Event** box.

This can be an arbitrary name.

- b. Select **WSA Support**. In the **WS-A Reply to** box, enter an IP address or **autodetect** to use the current host. Autodetect is useful when running the same script on several different machines. The server will reply to the specified location when the event occurs.
- c. Click **OK** to save the settings.
- d. Instruct the Vuser to wait for an event. Select **Insert > New Step** and add a **Web Service Wait For Event** step after the Web Service call step.
- e. Specify a step name, quantifier, and timeout. To add an event name, click **Add**. The Web Service will wait for the specified event before responding.
- f. Use the **Edit**, **Move Up**, and **Move Down** buttons to manipulate the events.

## **How to Define a Testing Method**

This task describes how to select a testing method.

### **1. Open the step properties**

In the Step Navigator, right-click the step whose response you want to test, and select **Show Arguments**.

### **2. Select an argument**

Select the Output Argument node. For details, see "New Web Service Call Dialog Box" on [page 865](#).

### **3. Select a testing method and choose an expected response**

- To perform negative testing only, select the **Negative Testing** check box and choose **SOAP Fault** as the **Expected Response**.
- To accept any type of SOAP response, select the **Negative Testing** check box and choose **Any SOAP** as the **Expected Response**.
- To perform positive testing only, clear the **Negative Testing** check box.

### **4. Verify function in the script**

In Script view, VuGen indicates the testing method with the **ExpectedResponse** argument. In the following example, the script performs negative testing, indicated by the **SoapFault** value:

```
web_service_call("StepName=AddAddr_101",
    "SOAPMethod=AddrBook|AddrBookSoapPort|AddAddr",
    "ResponseParam=response",
    "Service=AddrBook",
```

```

"ExpectedResponse=SoapFault",
"Snapshot=t1189409011.inf",
BEGIN_ARGUMENTS,
END_ARGUMENTS,
BEGIN_RESULT,
END_RESULT,
LAST);

```

## 5. Evaluate the SOAP fault value

When you replay a script that results in a SOAP fault, VuGen saves the fault to a parameter called **response**. To check the returned value of the SOAP fault, evaluate the **response** output parameter using **lr\_xml\_find**.

In the following example, **lr\_xml\_find** checks for a **VersionMismatch** SOAP fault and issues an output message.

```

lr_xml_find("XML={response}",
            "FastQuery=/Envelope/Body/Fault/faultString",
            "Value=VersionMismatch",
            LAST);
if (soap_fault_cnt >0)
    lr_output_message{"A Version Mismatch SOAP Fault occurred"}

```

For more information about **lr\_xml\_find**, see the Function Reference ([Help > Function Reference](#)).

## **How to Add a Database Connection**

This task describes how to add a database connection step through Tree view.

### 1. Open Solution Explorer

Select **View > Solution Explorer**.

### 2. Select a section

Select the desired section: **vuser\_init** or **Action**. To avoid repeating the connection sequence in every iteration, place it in the **vuser\_init** section.

### 3. Insert a database connection step

Select **Design > Insert in Script > New Step**. Choose the **lr\_db\_connect** step. The Database Connection dialog box opens. Specify a **Step Name**, **Connection Name**, and **Data Provider**, OLEDB or SQL.

### 4. Create a database connection string

- Click **Connection String Generator** to generate a database connection string specific to your environment.

- b. Indicate the connection properties:
  - o **Server Name**
  - o **Database Name**
  - o **Authentication** method: Windows Authentication or User/password.
  - o **Username and Password**
- c. Click **Test Connection** to verify that the information you provided is correct.
- d. Select an **SQL Provider**, OLEDB or SQL, and click **Generate**.

## 5. Verify function in the script

Check that an `Ir_db_connect` function was written to the script.

# How to Create a User Handler

This task describes how to write a user handler for your script.

## 1. Prerequisite - Create a Web Service call

Import a WSDL file and create a standard Web Service Call. For details, see "[Adding Web Service Script Content - Overview](#)" on page 848.

## 2. Define a user handler function

Define a user handler before the Web Service call:

```
int MyScriptFunction(const char* pArgs, int isRequest)
{
...
}
```

## 3. Call the user handler function

Call the handler function by specifying the function name as a value for the **UserHandlerFunction** argument. in the Web Service Call.

```
web_service_call(
...
"UserHandlerFunction=MyScriptFunction",
"UserHandlerArgs=<handler arguments>",


```

```
LAST);
```

#### 4. Evaluate the handler function

Evaluate the handler's return code to determine if it succeeded. Use the return codes as described in ["User Handlers" on page 889](#).

```
//This function processes the SOAP envelope before sending it to the server.
int MyScriptFunction(const char* pArgs, int isRequest)
{
    if (isRequest == 1) {
        //Get the request that is going to be sent
        char* str = lr_eval_string("{SoapEnvelopeParam}");
        //Manipulate the string...
        //Assign the new request content
        lr_save_string(str, "SoapEnvelopeParam");
        return LR_HANDLER_SUCCEEDED_AND_MODIFIED;
    }
    return LR_HANDLER_SUCCEEDED;
}
```

#### 5. Create a DLL file - optional

To define a user handler through a DLL, locate the API header file, **LrWsHandlerAPI.h** in the product's **include** folder.

You can use a sample Visual Studio project located in the samples/WebServices/SampleWsHandler folder as a template for creating a handler. The sample retrieves the request and response envelope and saves it to a parameter. To use this sample, open it in Visual Studio and modify it as required. If you do not need to save the request/response to a parameter, you can remove that section of the sample.

After editing the sample, save it and compile the DLL. When you compile the project, Visual Studio places the **<user\_handler\_name>.DLL** file in the **bin** folder. If you compile the project from another location, or if you want to copy the DLL from one machine to another, make sure to place it in the **bin** folder.

#### 6. Configure the user handler - optional

Declare the DLL user handler globally or locally.

To apply the user handler globally to all requests in the script, add the following section to the **default.cfg** file in the script's folder.

```
[UserHandler]
Function=<name>
Args=<arguments>
Order=<BeforeSecurity/AfterSecurity/AfterAttachments>
```

- **Name.** The name of the DLL.
- **Args.** A list of the configuration arguments for the handler. Use the **GetArguments** method to retrieve the arguments in your handler.
- **Order.** The order in which Vusers process the user handler in requests: **Before Security**, **After Security**, or **After Attachments**. You can also use this argument to override the transport layer, by entering the value **Replace Transport**.

**Note:** Setting the **UserHandlerFunction** property of a **web\_service\_call** function, overrides the definitions in the .cfg file.

By default, user handlers are processed before the security. For request messages, Vusers process the attachments handler after the security handler. For responses, Vusers process the handlers in a reversed order. In typical cases the order does not matter, so any value is acceptable.

To override the Transport layer, specify **Order=Replace Transport** and specify the new transport handler. If you implement the transport handler as a separate DLL, the **HandleRequest** function is called, while the **HandleResponse** function is ignored.

To use the handler locally, for a specific request, add the following arguments to the **web\_service\_call** function:

```
UserHandlerName=<name1>
UserHandlerArgs=<args1>
UserHandlerOrder=<BeforeSecurity/AfterSecurity/AfterAttachments/Replace
Transport>
```

## 7. Copy the user handler to all required machines

Make sure that the user handler DLL is accessible to all Load Generator machines running scripts that call it. You may, for example, copy it to the product's **/bin** folder.

If you copy the script to another machine, it retains the handler information, since it is defined in script's folder.

## 8. Implement the user handler - optional

To implement a user handler, you use the entry functions **HandleRequest** or **HandleResponse**. Both functions have a single parameter, **context**, whose properties you can set in your handler. Use the Get functions to retrieve properties, and Set functions to pass information from the replay framework to the handlers or between the handlers.

- **GetEnvelope.** Gets the envelope content. For example, example:  
`const char * pEnvelope = context->GetEnvelope();`
- **GetEnvelopeLength.** Gets the envelope length

- **SetEnvelope.** Sets the envelope content and length. For example:
 

```
string str("MySoapEnvelope...");  
context->SetEnvelope(str.c_str(), str.length());
```
- **SetContentType.** Sets a new value for HTTP header content type
- **LogMessage.** Issues a message to the replay log
- **GetArguments.** Gets the configuration arguments defined for the current handler in order to pass it to the DLL
- **GetProperty.** Gets a custom property value
- **SetProperty.** Sets a custom property value

For more information, see the comments in the **LrWsHandlerAPI.h** file located in the product's **include** folder.

## **How to Customize Configuration Files**

The following steps describe how to modify configuration files. For details, see "[Custom Configuration Files](#)" on page 891.

### **Locate the configuration file**

Determine the location of the configuration file. The standard .NET configuration file, **mmdrv.exe.config** is located in the product's **bin** folder. Some applications have their own file, **app.config**.

### **Save the application's configuration file**

If your application has its own **app.config** file:

- To apply the configuration information globally to all scripts, save the **app.config** file as **mmdrv.exe.config** in the **bin** folder, overwriting the existing file.
- To apply the configuration information locally, specifically for this script, copy the **app.config** file to the script's folder. This overrides the **mmdrv.exe.config** file, and remains associated with this script even when you copy it to other machines.

### **Set the security - optional**

By default, VuGen allows unsigned certificates to facilitate testing. To disallow unsigned certificates, modify the **allowTestRoot** flag in the **<security>** section to **false**.

```
<security>  
  <x509 storeLocation="currentuser" allowTestRoot="false"
```

## **Web Services Snapshots - Overview**

Vuser scripts based on the Web Services protocol utilize VuGen's Snapshot pane.

- For an introduction to the Snapshot pane, see "[Snapshot Pane - Overview](#)" on page 85.
- For details on how to work with the Snapshot pane, see "[How to Work with Snapshots](#)" on page 88.
- For details on the standard Snapshot pane UI, see "[Snapshot Pane](#)" on page 126.

The Snapshot pane enables you to view snapshots of Web service calls. When you display the Snapshot pane for a Web Services script, the left side of the Snapshot pane displays a tree view of the snapshot data; the right side of the Snapshot pane displays a text view of the snapshot data.

The tree view on the left of the Snapshot pane is composed of a number of nodes. An icon to the left of each node indicates the type of the node:

-  **Element:** Indicates that the node represents an element in the XML file.
-  **Attribute:** Indicates that the node represents an attribute in the XML file.
-  **Value:** Indicates that the node represents a value in the XML file.

In addition to the basic Snapshot pane functionality, the Snapshot pane for Web Services scripts includes additional functionality. The UI for this additional functionality is described below.

<b>To access</b>	Select <b>View &gt; Snapshot</b> , or click the <b>Show Snapshot Pane</b> button  on the VuGen toolbar.
<b>Relevant tasks</b>	<a href="#">"How to Prepare Scripts for Replay" on page 894</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 Response	Displays a snapshot of the SOAP response returned by the server.
 Request	Displays a snapshot of the SOAP request sent to the server by the Web Service call.
	Opens the XPath Search dialog box which enables you to perform an XPath search of the snapshot.
	Displays the previous or next results of the XPath search.
	Displays or hides the XML <b>attribute</b> nodes in the tree view of the snapshot.
	Displays or hides the XML <b>value</b> nodes in the tree view of the snapshot.

<b>&lt;shortcut menu&gt;</b>	<ul style="list-style-type: none"> <li>• <b>Copy Selection.</b> Copies the text that is selected in the text view to the clipboard.</li> <li>• <b>Search Community.</b> Performs a community search using the text that is selected in the text view as the search string. For details about performing a community search, see "<a href="#">Editor - Overview</a>" on page 82.</li> <li>• <b>Copy XPath.</b> In the tree view, copies the XPath of the selected node to the clipboard. In the text view, copies the XPath of the XML element in which the cursor is located to the clipboard.</li> <li>• <b>Copy full value.</b> In the tree view, copies the full XML code of the selected node to the clipboard. In the text view, copies the full XML code of the XML element in which the cursor is located.</li> <li>• <b>Insert XML Check.</b> Opens the Insert XML Check dialog box that enables you to insert an <b>XML Find</b> step into the Vuser script.</li> </ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>This option is available in the Response view only.</p> <p>This option is available for <b>attribute</b>  and <b>value</b>  nodes only.</p> </div> <ul style="list-style-type: none"> <li>• <b>Save value in parameter.</b> Opens the Save Value as Parameter dialog box that enables you to save the selected value to a simple parameter.</li> </ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>This option is available in the Response view only.</p> <p>This option is available for <b>attribute</b>  and <b>value</b>  nodes only.</p> </div> <ul style="list-style-type: none"> <li>• <b>Save XML in parameter.</b> Opens the Save Value as Parameter dialog box that enables you to save the selected value to an XML parameter.</li> </ul> <p style="margin-left: 20px;">This option is available in the Response view only.</p> <ul style="list-style-type: none"> <li>• <b>Create Correlation.</b> Opens the Correlation tab in the Design Studio. The text selected in the Snapshot pane appears as a manual correlation entry in the Design Studio. For details, see "<a href="#">How To Manually Correlate Scripts</a>" on page 282.</li> </ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>This option is available in the Response view only.</p> <p>This option is available for <b>attribute</b>  and <b>value</b>  nodes in the tree view, and when text is selected in the text view.</p> </div> <ul style="list-style-type: none"> <li>• <b>Create Correlation Rule.</b> Opens the Add as Rule dialog box that enables you to add the selected text as part of a correlation rule. For details, see "<a href="#">Correlation Tab [Design Studio] Overview</a>" on page 275.</li> </ul>
------------------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

	<p>This option is available in the Response view only.</p> <p>This option is available for attribute <math>=\#</math> and value <math>\#\#</math> nodes in the tree view, and when text is selected in the text view.</p>
--	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Database Connection Dialog Box

This dialog box helps you create a string to connect to your database.

<b>To access</b>	Click <b>Connection String Generator</b> in the Database Connection dialog box.
<b>Relevant tasks</b>	<a href="#">"How to Send Messages over JMS" on page 895</a>
<b>See also</b>	<a href="#">"Connection String Generator Dialog Box" below</a>

User interface elements are described below:

UI Element	Description
<b>Connection String Generator</b>	Opens the Connection String Generator. For details, see <a href="#">"Connection String Generator Dialog Box" below</a> .
<b>Step Name</b>	The name or IP address of the database server.
<b>Connection String</b>	The string by which to connect to the database. Use the <b>Connection String Generator</b> .
<b>Data Provider</b>	The SQL provider: <b>OLEDB</b> or <b>SQL</b> .

## Connection String Generator Dialog Box

This dialog box helps you create a string to connect to your database.

<b>To access</b>	Click <b>Connection String Generator</b> in the Database Connection dialog box.
<b>Relevant tasks</b>	<a href="#">"How to Send Messages over JMS" on page 895</a>
<b>See also</b>	<a href="#">"Database Connection Dialog Box" above</a>

User interface elements are described below:

UI Element	Description
<b>Test Connection...</b>	Tests the connection to the database.
<b>Generate</b>	Generates the database connection string and writes it in the <b>Connection String</b> field in the Database Connection dialog box.
<b>Server Name</b>	The name or IP address of the database server.

<b>DB Name</b>	The name of the database.
<b>Authentication</b>	The authentication method for the database: <b>Windows Authentication</b> or <b>User/password</b> . <ul style="list-style-type: none"><li>• <b>User Name, Password</b>. The credentials for the database.</li></ul>
<b>SQL Provider</b>	The SQL provider: <b>OLEDB</b> or <b>SQL</b> .


## Web Services - Managing Services

### ***Managing Services Overview***

The Service Management window lets you manage a list of service entries for the current script. You can view and set the properties of each service entry.

You add service entries to the list by importing WSDL files. When you add a WSDL to the list, VuGen creates a working copy that it saves with the script—it is not global. Therefore, for each script that you create, you must import the desired WSDL files.

The Service Management window provides quick access buttons for importing, deleting, and comparing services.



The tabs provide you with the ability to set the WSDL properties.

## Description

The **Description** tab displays information about the service:

- **Original location.** The original source of the WSDL file (read-only).
- **Service name.** The name of the Web Service (read-only).
- **Last update from original.** The last date that the local copy was updated from the original source (read-only). You can update the version manually or retrieve it automatically each time you reopen the test.
- **Service address.** An endpoint address to which the request is sent. If required, you can override the endpoint specified in the WSDL file.
- **Created by.** The name of the user who originally imported the service (read-only).

- **Toolkit.** The toolkit associated with the script. You set this before importing the first WSDL file (read-only).

## Operations

Each of the imported services may define multiple operations. The **Operations** tab indicates which operations are being used for the service selected in the left pane.

Operation Name	Port Name	Used In Script
AddAddr	AddrBookSoapPort	No
ChangeAddr	AddrBookSoapPort	No
DeleteAddr	AddrBookSoapPort	No
Export	AddrBookSoapPort	No
GetAddr	AddrBookSoapPort	No
GetNames	AddrBookSoapPort	No
Import	AddrBookSoapPort	No

## Connection Settings

In some cases WSDLs reside on secure sites requiring authentication. In certain instances, the WSDL is accessed through a proxy server.

VuGen supports the importing of WSDLs using security and WSDLs accessed through proxy servers. The following security and authentication methods are supported:

- SSL
- Basic and NTLM authentication
- Kerberos for the .NET toolkit

For more information about setting the connection information while importing the WSDL, see "[How to Add and Manage Services](#)" on page 912.

## UDDI Data

You can view the details of the UDDI server for each service that you imported from a UDDI registry.

The read-only information indicates the URL of the UDDI server, the UDDI version, and the Service key.

## Protocol and Security Settings

The Protocol and Security Settings tab shows the details of the security scenario applied to the script. If you did not choose a scenario, it uses the default <no scenario>. For more information, see "[How to Add and Manage Services](#)" on page 912.

This section also includes:

- "[Importing Services](#)" below
- "[Comparison Reports](#)" below

## ***Importing Services***

VuGen lets you import services for the purpose of creating a high-level tests with Web Service Call steps. Typically, you begin creating a script by importing a WSDL file.

The Import mechanism requires the following information:

- **Source.** The source of the WSDL: URL, File, UDDI, or Application Lifecycle Management. UDDI is a universal repository for services (Universal Description, Discovery, and Integration). Service brokers register and categorize published Web Services and provide search capabilities. The UDDI business registry is an example of a service broker for WSDL-described Web Services.
- **Location.** the path or URL of the WSDL, entered manually or by browsing.
- **Toolkit.** The toolkit to permanently associate with all services in the script for all subsequent imports and replays (only available for the first service added to the script). The toolkit setting instructs VuGen to send real client traffic using an actual toolkit—not an emulation.

VuGen supports the .NET Framework with WSE 2 version SP3 and Axis/Java based Web Services Framework toolkits. VuGen imports, records, and replays the script using the actual .NET or Axis toolkit. By default, VuGen uses automatic detection to determine the most appropriate toolkit.

- **Connection Settings.** Authentication or proxy server information. This setting is useful for WSDLs residing on secure servers, or WSDLs that must be accessed via a proxy server.

If VuGen detects a problem with your WSDL when attempting to do an import, it issues an alert and prompts you to open the report. The report lists the errors and provides details about them.

For task details, see "[How to Add and Manage Services](#)" on page 912.

## ***Comparison Reports***

VuGen lists the differences between the files in a Comparison report.

You can configure the comparison settings, indicating which items to ignore during the comparison. For more information, see the ["XML/WSDL Comparison Dialog Box" on page 918](#).

In WSDL Comparison reports, there are two columns—**Working Copy** and **Original File**. The Working Copy is the WSDL stored with the script, while the Original File is the WSDL at its original location—a network file path or a URL.

In XML Comparison reports, each column displays the path of an XML file.

The Comparison report uses the following legend to mark the differences between the two files:

- **Yellow**. Changes to an existing element (shown in both versions).
- **Green**. A new element added (shown in the original file copy).
- **Pink**. A deleted element (shown in the working copy).

In the following example, line 24 was deleted from the original copy and line 28 was added.

```

0:00:10 2005

Found 2 differences.

Working copy

<!-- Addr
<!-- Address
<!-- Name
<!-- Street
<!-- Apt
<!-- City
<!-- State
<!-- Zip
<!-- Phone-numbers
<!-- Reference
<!-- Type

Added line [green square] Deleted line [red square]

```

The screenshot shows a comparison window with the title "Found 2 differences." It has a "Working copy" tab selected. The XML code is displayed with line numbers on the right. Line 24, which contains the element `<element name="apt" type="string"/>`, is highlighted with a red background, indicating it was deleted from the working copy. Line 28, which contains the element `<element name="phone-numbers" type="typens:ArrayOfPhoneNumber" />`, is highlighted with a green background, indicating it was added to the working copy. Below the XML code, there are two buttons: "Added line" with a green square icon and "Deleted line" with a red square icon.

## Web Reference Analyzer

Many WSDL files reference other files such as XSD and other XML files. Before running a script, you may want to determine what these files are and if they are available.

VuGen's WSDL Reference Analyzer checks the WSDL for dependencies, and lists them in the WSDL Reference Analyzer window and in a log file.

The Analyzer places the WSDL and its dependent files in a zip archive file. It saves the dependency information to a log file, listing its path in the Analyzer window.

For user interface details, see ["WSDL Reference Analyzer Dialog Box" on page 919](#).

For task details, see ["How to Analyze WSDL Dependencies" on page 913](#).

## How to Add and Manage Services

This task describes how to create a list of services that you can call from your test. Using the Manage Services window, you import services and configure their settings.

### Open the Manage Services Dialog Box

Select **SOA Tools > Manage Services** or click the toolbar button to open the Manage Services dialog box.

### Import a Service

Click **Import**. In the Import Service dialog box, select a WSDL source and browse to the location.

For **URL** type imports, the Browse button opens a new browser. Navigate to the WSDL and then close the browser. This action places the URL in the location box. For details, see the "[Import Service Dialog Box](#)" on page 917.

If your service requires authentication or uses a proxy, configure these settings before importing the WSDL. Expand the Import Services dialog box and click **Configure**. For details, see the "[Connection Settings Dialog Box](#)" on page 916.

Repeat this step for all the services you want to include in your test.

### Get to Know the WSDL

Familiarize yourself with the WSDL. View its details as described in the "[Manage Services Dialog Box](#)" on the next page.

Click **View WSDL** to open the locally saved WSDL file in Internet Explorer and study its structure.

### Check for WSDL Updates - Optional

Use the Comparison tool to check that the WSDL did not change since your last import or update.

First, set the comparison options. Click **SOA Tools > SOA Settings > XML/WSDL Comparison**. Specify what differences to ignore. For details, see "[XML/WSDL Comparison Dialog Box](#)" on page 918.

In the Manage Services window, click **Compare** to open a report comparing the working copy of the WSDL with the one at the original location.

If you discover changes in the Comparison report, click **Update Now** to retrieve the latest version of the WSDL from its source.

### Override the Service Address- Optional

View the address in the **Service Address** box. This is the default endpoint address as retrieved from the WSDL. If you want to override it, select **Override address** and type in an alternate endpoint address for the service requests.

To return to the default address, clear the **Override address** option. For details, see the "[Manage Services Dialog Box](#)" on the next page.

### Set a Security Scenario - Optional

Click the **Protocol and Security** tab to use WS-Security or another type of a security scenario.

For more information, see "[Web Services - Security](#)" on page 919.

## How to Analyze WSDL Dependencies

This task describes how to use the Reference Analyzer to determine WSDL dependencies. For user interface details, see "[WSDL Reference Analyzer Dialog Box](#)" on page 919.

### 1. Open the Reference Analyzer

Select **SOA Tools > WSDL Reference Analyzer**.

### 2. Select a source and target

In the **Select WSDL file** box, indicate the location of the WSDL you want to analyze.

In the **Output file path** box, indicate a location for the zip file.

### 3. Begin the analysis

Click **Start Analyzing**. The Analyzer lists all of the dependencies in the output window along with their paths.

### 4. View the log

View the results in the log window. To clear the results and perform another analysis, click **Clear Log**.

## Manage Services Dialog Box

This dialog box enables you to manage your WSDLs, provide authentication information, and set a security scenario.

<b>To access</b>	Use one of the following:
	<ul style="list-style-type: none"> <li>Click the <b>Manage Services</b> button  on the VuGen toolbar.</li> <li><b>SOA Tools &gt; Manage Services</b></li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Add and Manage Services" on the previous page</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 Import	Opens the Import Service dialog box.
 Delete	Removes the selected service from the list.

 Compare	Opens the WSDL Comparison Report showing the Working copy and Original copy of the WSDL side-by-side. To set the comparison settings, see " <a href="#">XML/WSDL Comparison Dialog Box</a> " on page 918.
 View WSDL	Displays the WSDL in a browser.
<WSDL list>	A list of the imported WSDLs.
Description tab	Provides information about the WSDL, its endpoint address, toolkit, and update information.
Operations tab	Lists the operations of the service: <b>Operation Name</b> , <b>PortName</b> , and <b>Used in Script</b> (Yes or No). Click a column to sort the operations by that column's data. Click it again to reverse the sorting order.
Connection Settings tab	Allows you to provide authentication settings for the machine from which you are importing a service. For more information, see the " <a href="#">Manage Services Dialog Box</a> " on the previous page. <b>Note:</b> This only applies to URL and UDDI type imports.
UDDI Data tab	The UDDI server, UDDI version, and service key. For more information, see the " <a href="#">Manage Services Dialog Box</a> " on the previous page.
Protocol and Security tab	Allows you to view and set a security scenario for your Web Service calls. For more information, see below.

## Description Tab

The following elements are displayed in the **Description** tab:

UI Element	Description
 Update Now	Loads the latest version of the WSDL from its original location.
<b>Created By</b>	The name with which you logged in. You can edit this field and specify a different name. This is useful for sorting the services in reports (read-only).
<b>Description</b>	An editable field into which you can type information about the service.
<b>Last update from original</b>	The last date and time the WSDL was updated (read-only).
<b>Original Location</b>	The original location from where the WSDL was imported (read-only).

<b>Override address</b>	Enables you to enter an alternate endpoint for the service in the <b>Service Address</b> box.
<b>Service Address</b>	The endpoint of the service to which service requests are sent, retrieved from the WSDL file (read only). To override the default address, select <b>Override address</b> .
<b>Service Name</b>	The native service name in the WSDL file that is displayed by default when importing the service (read-only).
<b>Toolkit</b>	The toolkit associated with the service. You set this when you import the service (read-only).
<b>Update when opening script</b>	Updates the WSDL from its source each time you open the script.

## Connection Settings Tab

The following elements are included:

UI Element	Description
<b>Authentication</b>	<p><b>Use Authentication Setting:</b> Enables you to enter credentials for authentication.</p> <ul style="list-style-type: none"> <li><b>Username, Password.</b> The user name and password to use for retrieving the WSDL.</li> </ul> <p><b>Tip:</b> For users not in the default domain, type the domain name before the user name. For example, <code>domain1/alex_qc</code>.</p>
<b>Proxy</b>	<p><b>Use Proxy Setting.</b> Enables you to enter proxy details and credentials.</p> <ul style="list-style-type: none"> <li><b>Server.</b> Name or IP address of proxy server.</li> <li><b>Port.</b> Port through which to access the WSDL.</li> <li><b>Username, Password.</b> the user name and password to be used for authentication. For users not in the default domain, type the domain name before the user name. For example, <code>domain1/alex_qc</code>.</li> </ul>

## UDDI Data Tab

The following elements are included:

UI Element	Description

<b>Service Key</b>	A unique identifier of the service on the UDDI server, used to locate the service definition when updating the service.
<b>UDDI Server</b>	The URL address and version of the UDDI server from which the service definition is imported.
<b>UDDI Version</b>	The version of the UDDI registry: 2 or 3.

## Connection Settings Dialog Box

Enables you to provide authentication credentials and proxy server details for the machine hosting the WSDL file.

<b>To access</b>	<ul style="list-style-type: none"> <li>For a new service: Select <b>SOA Tools &gt; Manage Services</b>. Click the <b>Import</b> button. In the Import Services dialog box, click <b>Connection Settings</b>.</li> <li>For existing services: Select a service in the Mange Services dialog box, and click the <b>Connection Settings</b> tab.</li> </ul>
<b>Important information</b>	Only available for services imported through a URL and UDDI.
<b>Relevant tasks</b>	<a href="#">"How to Add and Manage Services" on page 912</a>

The following elements are included:

UI Element	Description
<b>Authentication</b>	<p><b>Use Authentication Setting:</b> Enables you to enter credentials for authentication.</p> <ul style="list-style-type: none"> <li><b>Username, Password.</b> the user name and password to use for retrieving the WSDL.</li> </ul> <p><b>Tip:</b> For users not in the default domain, type the domain name before the user name. For example, <code>domain1/alex_qc</code>.</p>
<b>Proxy</b>	<p><b>Use Proxy Setting.</b> Enables you to enter proxy details and credentials.</p> <ul style="list-style-type: none"> <li><b>Server.</b> Name or IP address of proxy server.</li> <li><b>Port.</b> Port through which to access the WSDL.</li> <li><b>Username, Password.</b> the user name and password to be used for authentication. For users not in the default domain, type the domain name before the user name. For example, <code>domain1/alex_qc</code>.</li> </ul>

## Import Service Dialog Box

Enables you to import WSDLs from a file system, a URL, Application Lifecycle Management, a UDDI, or Systinet.

<b>To access</b>	Use one of the following:
	<ul style="list-style-type: none"> <li>• Select <b>Services &gt; New &gt; Import Services</b></li> <li>• Select <b>New &gt; Import Services</b> from the shortcut menu</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Add and Manage Services" on page 912</a>

The following elements are included:

UI Element	Description
	<b>Browse.</b> Enables you to locate a service on the file system, through a browser, UDDI registry, or Application Lifecycle Management repository depending on your <b>Import WSDL from</b> selection.
<b>Connection Settings ...</b>	Opens the Connections Settings dialog box for configuring the authentication and proxy settings of the server hosting the WSDL. For details, see " <a href="#">Connection Settings Dialog Box</a> " on the previous page.
<b>Advanced Settings...</b>	Allows you to select a toolkit for the test. Choose <b>Automatic</b> , <b>.NET</b> , or <b>Axis</b> . The <b>Automatic</b> setting uses an algorithm to determine the most suitable toolkit.
<b>Import</b>	Begins the import process.
<b>Select WSDL from</b>	Location of WSDL. Browse for the information or enter it manually: <ul style="list-style-type: none"> <li>• <b>URL:</b> Complete URL. Make sure to insert a complete URL—not a shortened version.</li> <li>• <b>File:</b> Full path and file name.</li> <li>• <b>UDDI:</b> UDDI registry ID. The Browse button opens the "<a href="#">Search for Service in UDDI Dialog Box</a>" below.</li> </ul>

## Search for Service in UDDI Dialog Box

This dialog box enables you to locate a specific service from a UDDI registry.

<b>To access</b>	<ul style="list-style-type: none"> <li>In the Manage Services window, click <b>Import</b>.</li> <li>In the Import dialog box, select <b>UDDI</b> in the <b>Select WSDL from</b> section.</li> <li>Click .</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Add and Manage Services" on page 912</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Begins the search for a service based on the text in the <b>All or part of the service name</b> box.
<b>&lt;service list&gt;</b>	An alphabetical list of all the services that match the string. The grid shows the following columns: <b>Service Name</b> , <b>Service Key</b> , <b>Service Description</b> , <b>Service WSDL</b> .
<b>All or part of the service name</b>	A string including the desired service name or part of the name. You do not need to use wildcard expressions. The following options narrow the search: <ul style="list-style-type: none"> <li><b>Exact Match.</b> The service name must exactly match your text.</li> <li><b>Case Sensitive.</b> The case of service name must match the case of the specified text.</li> </ul>
<b>UDDI server inquiry address</b>	The complete path for the inquiry on the UDDI server.
<b>UDDI Version 2/3</b>	The UDDI version of the services to display in the list.

## XML/WSDL Comparison Dialog Box

This dialog box enables you to configure the settings for comparing different versions of a WSDL. You can instruct the comparison tool to ignore specific differences such as case, comments, and so forth.

<b>To access</b>	<b>SOA Tools &gt; SOA Settings &gt; XML/WSDL Comparison.</b>
<b>Relevant tasks</b>	<a href="#">"How to Add and Manage Services" on page 912</a>

User interface elements are described below:

UI Element	Description

, continued

<b>Show only differences</b>	Show only differences in the report—do not display the matching text.
<b>Ignore case</b>	Do not show case mismatches as differences.
<b>Ignore comments</b>	Do not mark mismatches in the comment as differences.
<b>Ignore processing instructions</b>	Do not mark mismatches in the processing instructions as differences.
<b>Ignore namespaces</b>	Do not mark mismatches in namespaces as differences.

## WSDL Reference Analyzer Dialog Box

This dialog box enables you to determine the dependencies of a WSDL file.

<b>To access</b>	<b>SOA Tools &gt; WSDL Reference Analyzer</b>
<b>Relevant tasks</b>	<a href="#">"How to Analyze WSDL Dependencies" on page 913</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Start Analyzing</b>	Begins the analysis, showing all the results in the Log window.
<b>Clear Log</b>	Clears the log window and log file.
<b>Open Containing Folder</b>	Opens the folder containing the output file.
<b>&lt;log window&gt;</b>	A running log of the reference analysis.
<b>Select WSDL file</b>	The local path or URL of the WSDL file to analyze.
<b>Output file path</b>	A location for the output zip file.

## Web Services - Security

### Setting Security Overview

When building Web Service applications, there is a challenge in building scalable applications that are secure. You can secure Web Services by having the message sent over a secure transport, such as Secure Sockets Layer (SSL), but this is limited to point-to-point communication.

To allow you to send your messages securely, VuGen supports several security mechanisms, Security Tokens (WS-Security), and SAML.

For more information on tokens, see below. For more information on SAML, see "[SAML Security Options](#)" on page 923.

The following table lists the considerations for using each of the models.

Legacy Model	Scenario Based Model
You are working with a script that already uses the legacy model	You are testing a WCF Service.
You are testing a service written in frameworks such as .NET 2.0, Axis, or other older toolkits	You are testing a service written in a new framework, such as Axis2 or Metro (WSIT).
You require a low-level control over WS-Security tokens	Your service uses advanced specifications such as WS-SecureConversation or WS-Trust.
You are having trouble using the new model or find the capabilities of the legacy more adequate for your needs	You are having trouble using the legacy model or you find the capabilities of the new model more adequate.

**Note:** If your WSDL is located in a secure location, you must provide the security information through the Manage Services dialog box. For more information, see the "[Connection Settings Dialog Box](#)" on page 916.

## Security Tokens and Encryption

The WS-Security specification lets you place security credentials in the actual SOAP message. You accomplish this by instructing a client to obtain security credentials from a source that is trusted by both the sender and receiver. When a SOAP message sender sends a request, those security credentials, known as **security tokens**, are placed in the SOAP message. When the Web server receives the SOAP request, it does not need to send additional requests to verify the integrity of the sender. The server verifies that the credentials are authentic before letting the Web Service execute the application. By not having to go back to the source of the credentials, this significantly improves the application's scalability.

To further secure Web Services, it is common to use digital signatures or encryption for the SOAP messages. Digitally signing a SOAP message verifies that the message has not been altered during transmission. Encrypting a SOAP message helps secure a Web Service by making it difficult for anyone other than the intended recipient to read the contents of the message.

The Web Services security mechanism associates security tokens with messages. This mechanism supports several security token formats to accommodate a variety of authentication requirements. For example, a client might need to provide a proof of identity or a security certificate.

To support WS-Security, VuGen allows you to create security tokens for your script. You can create multiple tokens and set their properties. After creating a token, you use it to sign or encrypt a SOAP message.

In certain instances, you do not send the token explicitly—you use the token for the purpose of signatures or encryption, without including the actual token in the SOAP envelope header. Using the **Add** option, you can indicate whether to send the actual token explicitly.

The available tokens are **Username and Password**, **X.509 Certificate**, **Kerberos Ticket**, **Kerberos2 Ticket**, **Security Context Token**, and **Derived Token**. The information you need to provide differs for each token.

- **User Name and Password.** The **User Name and Password** token contains user identification information for the purpose of authentication: **User Name** and **Password**.

You can also specify Password Options, indicating how to send the password to the server for authentication: **SendPlainText**, **SendNone**, or **SendHashed**.

- **X.509 Certificate.** This security token is a token based on an X.509 certificate. To obtain a certificate, you can either purchase it from a certificate authority, such as VeriSign, Inc. or set up your own certificate service to issue a certificate. Most Windows servers support the public key infrastructure (PKI) which enable you to create certificates. You can then have it signed by a certificate authority or use an unsigned certificate.

When you add an X.509 token to the Vuser script, you specify the **LogicalName**, **Store Name**, **Key identifier type**, **Key identifier value**, and **Store Location** arguments.

- **Kerberos Ticket/Kerberos2 Ticket.** (for Windows 2003 or XP SP1 and later) The Kerberos protocol is used to mutually authenticate users and services on an open and unsecured network. Using shared secret keys, it encrypts and signs user credentials. A third party, known as a KDC (Kerberos Key Distribution Center), authenticates the credentials. After authentication, the user may request a service ticket to access one or more services on the network. The ticket includes the encrypted, authenticated identity of the user. The tickets are obtained using the current user's credentials.

VuGen supports tokens based on both Kerberos and Kerberos2 security tokens. The primary difference between the Kerberos and Kerberos2 tokens is that Kerberos2 uses the Security Support Provider Interface (SSPI), so it does not require elevated privileges to impersonate the client's identity. In addition, the Kerberos2 security token can be used to secure SOAP messages sent to a Web Service running in a Web farm.

When you add a Kerberos token to the Vuser script, you specify a **LogicalName** for the token along with the **Host** and **Domain** names of the Web Services machine.

- **Security Context Token.** These tokens are security tokens that can be used repeatedly until they expire. SOAP message senders can use security context tokens to sign and/or encrypt a series of SOAP messages, known as a conversation, between a SOAP message sender and the target Web Service. The main benefits of this type of token are:
  - As long as the security context token has not expired, the SOAP message sender can use the same security context token to sign and/or encrypt the SOAP messages sent to the target Web Service.
  - Security context tokens are based on a symmetric key, making them more efficient at digitally

signing or encrypting a SOAP message than an asymmetric key.

- Security context tokens can be requested from one security token service by sending a SOAP message to another security token service.

When you add a **Security Context** token to the Vuser script, you specify values for the **LogicalName**, **Base Token**, **Issuer Token**, **End Point URI**, and **Add applies to** arguments.

- **Derived Token.** The Derived token is a token based on another existing token, excluding X.509 for which derivation is not supported. You need to specify a **LogicalName** and the **Derived From** token. If you remove the original token, then the derived token will no longer be available. Note that you cannot use a Derived type of token in a recursive manner.

For details about the token attribute in the script, see the Function Reference (**Help > Function Reference**).

## Adding the Security Policy

To add a security policy to a section of your script, you enclose the relevant steps with **Web Service Set Security** and **Web Service Cancel Security** steps.

When you add a **Web Services Set Security** step to your script, VuGen adds a **web\_service\_set\_security** function that contains arguments with the tokens, message signatures, and encryption that you defined.

```
web_service_set_security(
    SECURITY_TOKEN, "Type=USERNAME", "TokenName=mytoekn1",      "UserName=bob", "Password=123",
    "PasswordOptions=SendNone",      "Add=True", LAST);
```

Parameterization is not supported for the following arguments: **Token Type**, **Logical Name**, **Base Token**, **Issuer Token** or **Derive From** arguments.

## Working with Message Signatures and Encrypted Data

When you add a security token to a SOAP message, it is added to the SOAP message in the form of an XML element in the WS-Security SOAP header.

The message, however, is exposed and therefore requires additional security. This is especially true when the credentials, including the password, are sent in plain text as it is with role-based security.

The two methods used to secure the data are digital signatures and encryption.

- **Digital Signatures.** Digital Signatures are used by message recipients to verify that messages were not altered since their signing. The digital signature is usually in the form of XML within the SOAP message. The recipient checks the signature to make sure it is valid. Certain environments, such as WSE, automatically verify the signature on the SOAP recipient's computer.
- **Encryption.** Although the XML digital signature offers a mechanism for verifying that the message has not been altered since it was signed, it does not encrypt the SOAP message—the message is still plain text in XML format. To secure the message in order that it should not be

exposed, you encrypt it, making it difficult for an intruder to view and obtain a user's password.

Parameterization is not supported for message signatures and encryption arguments. For details on adding message signatures and encryption to your script, see "[How to Add Security to a Web Service Script](#)" on page 939.

## SAML Security Options

VuGen supports SAML (Security Assertion Markup Language) for Web Services. SAML is an XML standard for exchanging security-related information, called **assertions**, between business partners over the Internet. The assertions can include attribute statements, authentication, decision statements, and authorization decision statements.

SAML uses brokered authentication with a security token issued by STS (Security Token Service). The STS is trusted by the client and the Web Service to provide interoperable security tokens. SAML tokens are important for Web Service security because they provide cross-platform interoperability and a means of exchanging information between clients and services that do not reside within a single security domain.

You can set the SAML settings for an entire script or part of the script. For details, see "[How to Add SAML Security](#)" on page 940.

**Note:** You cannot apply SAML security and the standard Web Service (a **Web Service Set Security** step) security to the same step. To cancel Web Service security, insert a **Web Service Cancel Security** step.

### Signing SAML Assertions

VuGen provides a method for signing an unsigned SAML assertion. As input, you provide the unsigned assertion, a certificate file, and the optional password. As output, VuGen provides the signed SAML assertion. For task details, see "[How to Add SAML Security](#)" on page 940.

### Policy Files

SAML policy files follow the WSE 3.0 standard and define the attribute values for the SAML security. By default, VuGen uses the **samlPolicy.config** file located in the installation's **dat** folder.

When entering SAML security information, you can enter it manually in the properties dialog box, or you can refer to a policy file containing all of the security information. You can create your own policy file based on **samlPolicy.config**.

You can modify the policy file to include values for the security parameters, such as username and certificate information. When adding a SAML security step to your script, if you explicitly specify values for the security arguments, they override the values in the policy file.

If you make changes to the default policy file, we recommend that you copy the new policy file to your script's folder. Make sure to save custom policy files with a **.config** extension to insure that they remain with the script, even when running it on other machines or calling it from the LoadRunner Controller.

To learn more about the SAML policy files, see the SAML STS example on the MSDN Web site. If you want to emulate SAML Federation behavior, copy the **samlFederationPolicy.config** file from the data folder to your script's folder, and specify it as the policy file.

## **Security Scenarios Overview**

VuGen allows you to test Web Services that utilize advanced security and WS-Specifications. Such services can be written in various platforms such as WCF (Windows Communication Foundation), Metro (WSIT), and Axis2. For WCF services, VuGen also supports proprietary standards and transports.

You enable this support by setting up a security scenario. Each scenario represents a typical environment used in conjunction with Web Service calls. VuGen provides several built-in security scenarios that are commonly used. It applies the scenario's settings individually to each service.

For the built-in scenarios, the user interface lets you provide identity information where required. You can customize security, transport, proxy, and other advanced settings.

If you cannot find a scenario that corresponds to your environment, you can use the generic custom scenario.

For a "How To" guide on selecting a scenario, see [Tips and Guidelines](#).

## **Choosing a Security Model**

VuGen supports two models for configuring security for your Web Service calls: *Legacy* and *Scenario*. This chapter describes the Scenario security model. The Legacy model refers to the manual addition of Web Service Set Security steps, or the **web\_service\_set\_security** function.

The following table lists the considerations for using each of the models.

Legacy Model	Scenario Based Model
You are working with a script that already uses the legacy model	You are testing a WCF Service
You are testing a service written in frameworks such as .NET 2.0, Axis, or other older toolkits	You are testing a service written in a new framework such as Axis2 or Metro (WSIT).
You require a low-level control over WS-Security tokens	Your service uses advanced specifications such as WS-SecureConversation or WS-Trust
You are having trouble using the new model or find the capabilities of the legacy functions adequate	You are having trouble using the legacy model or you find the capabilities of the new model more adequate

## **Private, Imported, and Shared Scenarios**

To assign a security scenario to a specific service, use the Manage Services window. The **Protocol and Security** tab contains the interface to create and view security scenarios for individual services.

You can select a scenario in three ways:

- **Private scenario.** Create a new scenario by selecting one of the built-in ones and customizing it for your Web Service.
- **Imported scenario.** Use a scenario created at an earlier time. The scenario will be editable, and if someone modifies the original scenario, it will not affect you.
- **Shared scenario.** Load a security scenario already configured by another user from a remote location or the file system. You cannot edit this scenario's settings from the Manage Services window. If someone edits the scenario, it will affect your environment. You usually use this option after working with the product for some time and saving the scenario files.

## **Scenario Categories**

The scenario describes the configuration of your Web Service. It contains information such as security, encoding, proxy, and so forth. VuGen provides a Security Scenario editor that allows you to configure the settings for each scenario.

To determine the scenario that best fits your service, refer to the sections below. If you are unsure which scenario to choose, we recommend to use the **Custom Binding** scenario. For more information, see "[The Custom Binding Scenarios](#)" on page 930.

Use the default <no scenario> for:

- simple Web Services where no advanced standards are required.
- scripts that use the legacy security model
- Web Services that require a specific security setting, not available in any of the existing scenarios.

If you select a built-in scenario and experience problems in replay, it is possible that no scenario was required and the problem is elsewhere. Reset the value to <no scenario>.

The built-in security scenarios are divided into the following categories:

### **Core Scenarios**

The following table describes the built-in Core scenario.

Scenario Name	When to use

Plain SOAP	<ul style="list-style-type: none"> <li>• Web services which do not require advanced standards</li> <li>• Web services which may require you to specify the WS-Addressing version</li> </ul>
------------	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

For this type of scenario, if your service uses WS-Addressing, specify the version.

## Security Scenarios

The following table describes the built-in Security scenario.

Scenario Name	When to use
Username Authentication	<ul style="list-style-type: none"> <li>• Client is authenticated with a username and password on the message level</li> </ul>

For this type of scenario, specify the username/password, and if your service uses WS-Addressing, specify the version.

## WCF Scenarios

The following table shows the scenarios for Web Services that utilize WCF. The WSHttpBinding-based scenarios are divided according to the way the client authenticates itself to the server. For example, if your client presents a user name and a password to the server, choose the **Username (message protection)** scenario. The user interface lets you provide the identity information in the form of a user name or a certificate as required.

WCF Scenario Name	When to use
WSHttpBinding - No Authentication	<ul style="list-style-type: none"> <li>• Client uses the server's X.509 certificate for encryption</li> <li>• Client is not authenticated</li> <li>• Communication may utilize advanced standards such as secure conversation and MTOM</li> </ul>
WSHttpBinding - Windows authentication	<ul style="list-style-type: none"> <li>• Client and server use Windows authentication</li> <li>• Security is based on Kerberos or SPNEGO negotiations</li> <li>• Communication may utilize advanced standards such as secure conversation and MTOM</li> </ul>

wsHttpBinding - Certificate authentication	<ul style="list-style-type: none"> <li>Client uses the server's X.509 certificate for encryption</li> <li>Client uses its own X.509 certificate for signature</li> <li>Communication may utilize advanced standards such as secure conversation and MTOM</li> </ul>
WSHttpBinding - username (message protection) authentication	<ul style="list-style-type: none"> <li>Client uses the server's X.509 certificate for encryption</li> <li>Client is authenticated with a username and password</li> <li>Communication may utilize advanced standards such as secure conversation and MTOM</li> </ul>
WSHttpBinding - username (transport protection) authentication	<ul style="list-style-type: none"> <li>SSL is enabled</li> <li>Client is authenticated with a username and password</li> <li>Communication may utilize advanced standards such as secure conversation and MTOM</li> </ul>
WSFederationHttpBinding	<ul style="list-style-type: none"> <li>Client authenticates against the STS using a predefined scenario</li> <li>Client uses the token given from the STS to authenticate against the server</li> </ul>
Custom Binding	<ul style="list-style-type: none"> <li>Web Service that uses WS-* standards</li> <li>WCF services of any configuration</li> </ul>

## Optimization Scenarios

The following table describes the built-in Optimization scenario.

Scenario Name	When to use
MTOM	<ul style="list-style-type: none"> <li>MTOM enabled Web services</li> <li>Web Services which may require you to specify the WS-Addressing version</li> </ul>

For MTOM type scenarios, if your service uses WS-Addressing, specify the version.

## WCF Scenario Settings

This section describes the values required for the WCF security scenarios:

## The WsHttpBinding Scenario

### No Authentication (Anonymous)

In this scenario, the client uses the server's certificate to encrypt a message; there is no client authentication.

You specify only one of the following settings:

- **Negotiate service credentials.** Negotiate the Web Service's certificate with the server.
- **Specify service certificate.** Browse for a service certificate. For more information, see "[Select Certificate Dialog Box](#)" on page 948. If you select this option, the **Negotiate service credentials** option is not available.

Provide the DNS information.

- **Expected server DNS.** The expected identity of the server in terms of its DNS. This can be **localhost**, an IP address, or a server name. It can also be the common name by which the certificate was issued.

### Windows Authentication

This WCF scenario uses Windows Authentication.

You declare the expected identity of the server in terms of its **SPN** or **UPN** identities. If you are testing a WCF service that has not been customized and uses the default configuration, use this type of scenario.

### Certificate Authentication

In this WCF WSHtpBinding scenario, the client uses the server's X.509 certificate to encrypt the message and its own certificate for a signature.

Specify only one of the following settings:

- **Negotiate service credentials.** Negotiate the Web Service's certificate with the server.
- **Specify service certificate.** Browse for a service certificate. For details, see "[Select Certificate Dialog Box](#)" on page 948. If you select this option, the **Negotiate service credentials** option is not available.

Provide the DNS information:

- **Expected server DNS.** The expected identity of the server in terms of its DNS. This can be **localhost**, an IP address, or a server name. It can also be the common name by which the certificate was issued.

### Username Authentication (Message Protection)

In this WCF WSHtpBinding scenario, the client uses the server's X.509 certificate to encrypt the message, and sends a user name and password to authenticate itself.

Specify the following settings:

- **Username. Password.** The client's user name and password credentials.

Specify only one of the following settings:

- **Negotiate service credentials.** Negotiate the Web Service's certificate with the server.
- **Specify service certificate.** Browse for a service certificate. For details, see "[Select Certificate Dialog Box](#)" on page 948. If you select this option, the **Negotiate service credentials** option is not available.

Provide the DNS information:

- **Expected server DNS.** The expected identity of the server in terms of its DNS. This can be **localhost**, an IP address, or a server name. It can also be the common name by which the certificate was issued.

### **Username (Transport Protection) Authentication**

This WCF WSHttpBinding scenario enables SSL and authenticates the client with a user name and password on the message level.

Specify the following settings:

- **Username. Password.** The client's user name and password credentials.

### ***The Federation Scenario***

In the **WSFederationHttpBinding** scenario, the client authenticates against the STS (Security Token Service) to obtain a token. The client uses the token to authenticate against the application server.

Therefore, two bindings are needed, one against the STS and another against the application server.

First, use the Security Scenario editor to define an STS binding. For more information, see "[How to Create and Manage Security Scenarios](#)" on page 940. When setting the binding against the application server, specify this file in the **Referenced file** box.

For the Federation scenario, specify the following server information:

- **Transport.** HTTP or HTTPS
- **Encoding.** Text or MTOM

For the Federation scenario, specify the following security information:

- **Authentication mode.** IssuedToken, IssuedTokenForCertificate,

IssuedTokenForSslNegotiated, IssuedTokenOverTransport, or SecureConversation

- **Bootstrap policy.** IssuedToken, IssuedTokenForCertificate, IssuedTokenForSslNegotiated, or IssuedTokenOverTransport

For the Federation scenario, specify the following identity information:

- **Server certificate.** Browse for a server certificate. For more information, see the "[Select Certificate Dialog Box](#)" on page 948.
- **Expected server DNS.** the expected identity of the server in terms of its DNS. This can be **localhost** or an IP address or server name.

For the Federation scenario, specify the following STS (Security Token Service) information:

- **Issuer address.** The address of the issuer of the STS. This can be **localhost**, an IP address, or a server name.
- **Referenced binding.** The file that references the binding that contacts the STS (Security Token Service)

## ***The Custom Binding Scenarios***

The **Custom Binding** scenario enables the highest degree of customization. Since it is based upon WCF **customBinding**, it allows you to test most WCF services, along with services on other platforms such as Java that use WS - <spec\_name> specifications.

Use the **Custom Binding** scenario to configure a custom scenario that does not comply with any of the predefined security scenarios.

For the Custom Binding scenario, specify the following server information:

- **Transport.** HTTP, HTTPS, TCP, or NamedPipe
- **Encoding.** Text, MTOM, or WCF Binary

Specify the following security information:

- **Authentication mode.** None, AnonymousForCertificate, AnonymousForSslNegotiated, CertificateOverTransport, Kerberos, KerberosOverTransport, MutualCertificate, MutualSslNegotiated, SecureConversation, SspiNegotiated, UserNameForCertificate, UserNameForSslNegotiated, UserNameOverTransport, or SspiNegotiatedOverTransport
- **Bootstrap policy.** For SecureConversation type authentication, specify a bootstrap policy: AnonymousForCertificate, AnonymousForSslNegotiated, CertificateOverTransport, Kerberos, KerberosOverTransport, MutualCertificate, MutualSslNegotiated, SspiNegotiated,

UserNameForCertificate, UserNameForSslNegotiated, UserNameOverTransport, or SspiNegotiatedOverTransport

- **Net security.** the network security. Select None, Windows stream security, or SSL stream security. For services with HTTP transport, leave the default value, **None**. To enable SSL for HTTP, choose the HTTPS transport.

If your Web Service uses **Reliable messaging**, enable the option, and select **Ordered** or **Not Ordered**.

## Identities

Your security settings may require you to provide identity details for either the client and server, or both of them.

An example of identity details for the client, are user name/password or an **X.509** certificate.

For identity information, provide one or more authentication details as required by the service:

**Username, Password, Server certificate, Client certificate**, or a custom Windows identity. For details about choosing a certificate, see "[Select Certificate Dialog Box](#)" on page 948.

Some scenarios require you to declare the expected identity of the server in terms of its DNS, SPN, or UPN identity.

- **DNS.** Provide the name of a server or use localhost.
- **SPN.** Provide the SPN identity in the domain\machine format.
- **UPN.** Provide the UPN identity in the user@domain format.

After setting the basic values, you can set advanced attributes as described in "[Advanced Scenario Setting](#)" below.

## Advanced Scenario Setting

This section describes the Advanced scenario settings to customize a security scenario in the areas of Encoding, Advanced Standards, Security, or HTTP and Proxy.

Not all settings are relevant for all scenarios, so some of them might be disabled or hidden depending on the scenario.

### Encoding

The Encoding tab lets you indicate the type of encoding to use for the messages: **Text**, **MTOM**, or **Binary**. The default is **Text** encoding.

For each of these encoding methods, you can choose a version of WS-Addressing:

- None
- WSA 1.0

- WSA 04/08

## Advanced Standards

This tab lets you configure advanced WS- standards, such as Reliable Messaging and the Via address option.

If your service implements the **WS-ReliableMessaging** specification, enable the **Reliable Messaging** option and set the following options:

- **Reliable messaging ordered.** indicates whether the reliable session should be ordered
- **Reliable messaging version.** WSReliableMessagingFebruary2005 or WSReliableMessaging11

## Via Address

In certain instances, you may need to send a message to an intermediate service that submits it to the actual server. This may also apply when you send the message to a debugging proxy. This corresponds to the WCF **clientVia** behavior.

In such cases it may be useful to separate the physical address to which the message is actually sent, from the logical address for which the message is intended. The logical address may be the physical address of the final server or any name. It appears in the SOAP message as follows:

```
<wsa:Action>http://myLogicalAddress<wsa:Action>
```

The logical address is retrieved from the user interface. By default, it is the address specified in the WSDL. You can override this address from the Manage Services dialog box.

## Security

The Advanced security settings correspond to the **WS-Security** specifications.

For security scenarios that are based upon WCF WSHttpBinding, you can indicate the following settings:

- **Enable secure session.** Establish a security context using the WS-SecureConversation standard.
- **Negotiate service credentials.** Allow WCF proprietary negotiations to negotiate the service's security.

For **WSHttpBinding**, **Custom Binding**, or **WSFederationHttpBinding** WCF type scenarios, you can set the default algorithm suite and protection level:

Attribute	Meaning	Possible Values
-----------	---------	-----------------

<b>Default Algorithm Suite</b>	The algorithm to use for symmetric/asymmetric encryption. These are the values from the SecurityAlgorithmSuite configuration in WCF:	<ul style="list-style-type: none"> <li>• Basic128</li> <li>• Basic128Rsa15</li> <li>• Basic128Sha256</li> <li>• Basic128Sha256Rsa15</li> <li>• Basic192</li> <li>• Basic192Rsa15</li> <li>• Basic192Sha256</li> <li>• Basic192Sha256Rsa15</li> <li>• Basic256</li> <li>• Basic256Rsa15</li> <li>• Basic256Sha256</li> <li>• Basic256Sha256Rsa15</li> <li>• TripleDes</li> <li>• TripleDesRsa15</li> <li>• TripleDesSha256</li> <li>• TripleDesSha256Rsa15</li> </ul>
<b>Protection Level</b>	Should the SOAP Body be encrypted/signed	None, Sign, and EncryptAndSign (default)

For **Custom Binding** or **WSFederationHttpBinding** WCF type scenarios, you can customize the security settings in greater detail. The following table describes the options and their values:

Attribute	Meaning	Possible Values
Message Protection Order	The order for signing and encrypting	<ul style="list-style-type: none"> <li>• SignBeforeEncrypt</li> <li>• SignBeforeEncrypt-AndEncryptSignature</li> <li>• EncryptBeforeSign</li> </ul>
Message Security Version	The WS-Security security version	A list of the current versions

Security Header Layout	The layout for the message header	<ul style="list-style-type: none"> <li>• Strict</li> <li>• Lax</li> <li>• LaxTimeStampFirst</li> <li>• LaxTimeStampLast</li> </ul>
Key Entropy Mode	The entropy mode for the security key.	<ul style="list-style-type: none"> <li>• Client Entropy</li> <li>• Security Entropy</li> <li>• Combined Entropy</li> </ul>

You can enable or disable the following options:

- **Require derived keys.** Indicates whether or not to require derived keys.
- **Require security context cancellation.** Disabling this option implies that stateful security tokens will be used in the **WS-SecureConversation** session (if enabled).
- **Include timestamp.** Includes a timestamp in the header.
- **Allow serialized token on reply.** Enables the reply to send a serialized token.
- **Require signature confirmation.** Instructs the server to send a signature confirmation in the response.

For X.509 certificates, you can specify values for the following items:

Attribute	Meaning	Possible Values
<b>X509 Inclusion Mode</b>	When to include the X509 certificate	<ul style="list-style-type: none"> <li>• Always to Recipient</li> <li>• Never</li> <li>• Once</li> <li>• AlwaysToInitiator</li> </ul>
<b>X509 Reference Style</b>	How to reference the certificate	<ul style="list-style-type: none"> <li>• Internal</li> <li>• External</li> </ul>
X509 require derived keys	Should X509 certificates require derived keys	<ul style="list-style-type: none"> <li>• Enable - Yes</li> <li>• Disable - No</li> </ul>

X509 key identifier clause type	The type of clause used to identify the X509 key.	<ul style="list-style-type: none"> <li>• Any</li> <li>• Thumbprint</li> <li>• IssuerSerial</li> <li>• SubjectKeyIdentifier</li> <li>• RawDataKeyIdentifier</li> </ul>
---------------------------------	---------------------------------------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------

## HTTP and Proxy

This tab lets you set the HTTP and Proxy information for your test.

### HTTP(S) Transport

The following table describes the HTTP(S) Transport options:

Option	Meaning	Possible Values
<b>Transfer mode</b>	The transfer method for requests/responses	Buffered, Streamed, StreamedRequest, StreamedResponse
Max response size (KB)	The maximum size of the response before being concatenated	Default 65 KB
<b>Allow cookies</b>	Enable cookies	Enabled/Disabled
<b>Keep-Alive Enabled</b>	Enable keep-alive connections	Enabled/Disabled
<b>Authentication scheme</b>	HTTP authentication method	None, Digest, Negotiate, NTLM, IntegratedWindows Authentication, Basic, Anonymous
Realm	The realm of the authentication scheme	Any URL
<b>Require client certificate</b>	For SSL transport, require a certificate	Enabled/Disabled

### Proxy Information

If the Web service's transport uses a proxy server, you can specify its details in the **Security** tab. The following table describes the proxy options:

Option	Meaning	Possible Values
<b>Use default web proxy</b>	Use machine's default proxy settings	Enabled/Disabled

<b>Bypass proxy on local</b>	Ignore proxy when the service is on the local machine	Enabled/Disabled
<b>Proxy address</b>	the proxy server	Any URL
<b>Proxy authentication scheme</b>	HTTP authentication method on Proxy	None, Digest, Negotiate, NTLM, IntegratedWindows Authentication, Basic, Anonymous

## **WCF Extensibility**

You can implement your own binding, behavior, or channel when using customBinding by defining the assemblyPath and typeName by modifying the configuration file <script directory>/WSDL/@config/[your config].stss.

The assemblyPath attribute should have a value of either the full path of the dll or its relative path to script directory.

The typeName attribute should have the full type name: ns.typeName.

### **Binding**

Name the scenario attribute in the protocols element and provide the assemblyPath and typeName attributes.

The class you use for binding is inherited from System.ServiceModel.Channels.Binding.

### **Channel**

Add a new element under the customization node. You can specify any name for the element, however the element must contain the two attributes:assemblyPath and typeName.

The class to use for binding is inherited from System.ServiceModel.Channel.BindingElement.

**Note:** This will work with customBinding scenarios only.

### **Behavior**

Add a new element under the behaviors element (which is under endpointBehavior) and add the two attributes assemblyPath and typeName.

To bind the new element, implement the System.ServiceModel.Description.IEndpointBehavior class.

**Note:** If you inherit from System.ServiceModel.Description.ClientCredentials, the client credentials from this class will be used.

### **Examples of Channel and Behavior**

```
<protocols scenario="customBinding" uiType="customBinding" xml
```

```
ns="http://hp/ServiceTest/config">
<mode>Private</mode>
<customization>
<textMessageEncoding />
<preferLrHttpTransport />
<myChannel assemblyPath="CustomChannel.dll" typeName="CustomChannel.WCFChann
el" />
</customization>
<behaviors>
<endpointBehaviors>
<behavior>
<clientVia viaUri="qwqwq" />
<myBehavior assemblyPath="CustomBehavior.dll" typeName="CustomBehavior.WCFbe
ahvior" />
</behavior>
</endpointBehaviors>
</behaviors>
</protocols>
```

An example of overriding the whole binding (the configuration may contain just one line):

```
<protocols scenario="userBinding" assemblyPath="WCFBinding.dll" typeName=" W
CFBinding.Binding"/>
```

## ***Preparing Security Scenarios for Running***

### ***Parameterizing Security Elements***

You can parameterize the security elements in a script independently. For example, in a username-based security scenario, you might want each Vuser or iteration to use a different user name.

### ***Protecting Custom Headers***

When an operation uses SOAP headers, VuGen does not automatically sign or encrypt them. To incorporate a protection scheme such as a signature or encryption, you must manually add the following information to the scenario's configuration file (.stss) in the **behavior** element:

- soapAction of the relevant operation
- The header XML name and namespace
- The protection level

The following example shows an outgoing message with the soapAction, **http://mySoapAction**. The XML element **header1** from namespace **http://myServiceNamespace** is encrypted and signed. The **header2** element from the same namespace is only signed.

```
<protocols ...>
    ...
    <behaviors>
        <contractBehaviors>
            <behavior>
                <channelProtectionBehavior>
                    <protectionRequirements action="http://mySoapAct
ion">
                        <incomingEncryptionParts>
                            <header localName="header1" namespace="h
ttp://myServiceNamespace" />
                        </incomingEncryptionParts>

                        <incomingSignatureParts>
                            <header localName="header1" namespace=""
http://myServiceNamespace " />
                            <header localName="header2" namespace=""
http://myServiceNamespace " />
                        </incomingSignatureParts>
                    </protectionRequirements>
                </channelProtectionBehavior>
            </behavior>
        </contractBehaviors>
    </behaviors>
</protocols>
```

## ***Emulating Users with Iterations***

Many of the security scenarios establish a session with the server. For example, every scenario that uses **WS-SecureConversation** establishes a server session. This session is established when the first operation is executed and ends when the script is finished. By default, VuGen closes all sessions after each iteration and opens them again when the next iteration begins. This implies that every iteration simulates a new session and Vuser.

When working with multiple iterations, this may not be the desired effect—you may prefer to keep the original session active and not open a new session for each iteration. This applies when load

testing through the LoadRunner Controller or when setting multiple iterations in the run-time settings.

You can override this behavior so that only the first iteration will establish a new session, while all subsequent ones will continue to use the open session. This simulates a user who repeatedly performs an action using the same session.

To determine which simulation mode to use, choose the one which is most appropriate to what you are simulating. For example, if you are simulating a load test where most of the actions are performed repeatedly by the same user in a single session, use the above configuration. If you are unsure, leave the default settings.

## **How to Add Security to a Web Service Script**

This task describes how to add set the security for your Web Service calls. For details about Web Services security, see "[Setting Security Overview](#)" on page 919.

### **Insert a new Web Services Security Step**

1. Place the cursor at the point at which you want to add the security settings. In most cases, it is best to place it in **vuser\_init** so that the security scope will be applied to the whole script. To apply the security for specific calls, place it at the desired location.
2. Select **Insert > New Step** to open the Add Step dialog box.
3. Select **Web Service Set Security** and click **OK**. The Set Security Properties box opens.

### **Add a token - optional**

1. Click **Add** to add a new token. The Add Token dialog box opens.
2. Select a token type. For details, see "[Security Tokens and Encryption](#)" on page 920.

In the **LogicalName** box, assign an arbitrary name for the token to be used by VuGen in identifying the token.

Add any relevant information, such as **User Name** and **Password** for the User Name and Password type token.

To send the token explicitly in the SOAP envelope header, select **True**. To exclude the token from the SOAP envelope header, select **False**.

### **Add a message signature or encryption - optional**

1. Click **Add > Message Signature** or **Add > Encrypted Data**.
2. Select a token to use with the message signature or encryption. Both signatures and encryptions require you to specify a token previously defined as the signing/encrypting token.
3. Specify a target token, or leave the field blank to apply the signature or encryption to the whole message body. For details, see "[Security Tokens and Encryption](#)" on page 920.

### Set a message timeout - optional

To specify a time for which the message packet is considered valid, select **Time To Live** and specify a time in seconds.

### Cancel the security settings - optional

To cancel the security settings at a specific point within the script, add a **Web Service Cancel Security** step at the desired point.

## How to Add SAML Security

This task describes how to add SAML security for your Web Service calls. For more information about SAML security, see "[SAML Security Options](#)" on page 923.

For syntax information, see the Function Reference ([Help > Function Reference](#)).

### 1. Insert a new Web Services Security step

- a. Place the cursor at the point at which you want to add the security settings.
- b. Select **Insert > New Step** to open the Add Step dialog box.
- c. Select **Web Service Set Security SAML** and click **OK**. The properties box opens.

### 2. Insert a SAML assertion

To add a SAML assertion method, add a **Web Service Sign SAML Assertion** step through the Add Step dialog box (**Insert > New Step**). Provide the unsigned assertion, a certificate file, and a password (optional).

### 3. Set the security policy - optional

Specify a policy file, or leave it blank to use the default. If you manually enter values, they override any values in the policy file. You must provide an Issuer URL, also known as the **STS URL**.

### 4. Cancel the SAML settings - optional

To remove the settings at a specific point in the script, insert a **Web Service Cancel Security SAML** step.

## How to Create and Manage Security Scenarios

The following steps describes how to create and customize a security scenario for a specific service.

### 1. Open the Security Scenario Data dialog box

- a. Click **Manage Services**. In the left pane, select the service for which you want to set the security scenario. If necessary, import a service, as described in "[Import Service Dialog Box](#)" on page 917.

- - 
  - b. Select the **Protocol and Security** tab and click the **Edit Data** button. The Security Scenario Data dialog box opens.
2. **Create a scenario (if you do not have existing ones)**
- a. Choose **Private scenario** and select a built-on security scenario for the current service.
  - b. In the **Scenario type** box, choose a scenario. For details, see "[Choosing a Security Model](#)" on page 924.
  - c. Specify the required values for your scenario. For details, see "[WCF Scenario Settings](#)" on page 927.
  - d. To specify a certificate (only applicable to some of the scenarios), click the Browse button adjacent to the **Client certificate** or **Specify service certificate** box to open the Select Certificate dialog box. For details, see the "[Select Certificate Dialog Box](#)" on page 948.
    - o To retrieve a certificate from a file, choose **File** and locate its path.
    - o To retrieve a certificate from a Windows store, Choose **Windows Store**. Select a Store location and name. Specify a search string—to search for all certificates, leave the **Search text** box empty. To search for a specific certificate, specify a substring of the certificate name. If required, specify a password for the private key. Click **Find** to generate the list of certificates found in the store.

3. **Load a security scenario (if you have existing ones)**

- a. To use an existing scenario with the ability to modify it, choose **Private scenario**. Click **Import**. In the Shared Scenario dialog box, select a stored scenario. If required, modify the settings as described in "[WCF Scenario Settings](#)" on page 927.
- b. To use an existing scenario without the option of changing it, choose **Shared Scenario**. Use the Browse button to open the Shared Scenario dialog box and select a stored scenario.

**Note:** If someone modifies a shared scenario file at its source, it will affect your script.

4. **Configure advanced settings - optional**

Click **Advanced** to configure the Proxy, Encoding, and other advanced setting. For most scenarios, the default settings are ideal. For details, see "[Advanced Scenario Setting](#)" on page 931. Click **OK** to save the security scenario.

5. **Modify an existing security scenario - optional**

To create and modify security scenarios that will be available globally for all scripts—not just this specific service, use the Security Scenario editor. You can also use the editor to save the scenario so that others may load it.

- a. Choose **SOA Tools > Security Scenario Editor**.
  - b. Click the **Load** button and browse for an existing **stss** scenario file.
  - c. Modify the scenario settings as required
  - d. Click **Save** or **Save as**.
- 6. Protect SOAP headers - optional**
- Manually modify the **behavior** element in the scenario's configuration file
- a. In VuGen, open the Script view. Choose choose **View > Script View**.
  - b. Click in the script editor and select **Open Script Directory** from the shortcut menu.
  - c. Locate the security scenario's configuration file `<service_name>.stss` in **WSDL/@config** folder.
  - d. Modify the behavior section of the file. For details, see "[Protecting Custom Headers](#)" on [page 937](#).

## **7. Set the iteration mode- optional**

To configure your environment to use the same session for all iterations:

- a. Open the script root folder: In Script view, click inside the script and choose **Open Script Directory** from the shortcut menu.
- b. Open **default.cfg** file in a text editor.
- c. In the **[WebServices]** section, add in a row under the toolkit. If you are using the Axis toolkit or if you configured other settings, the file contents may differ.

```
[WebServices]
Toolkit=.NET
SimulateNewUserInNewIteration=0
```

- d. Save and close the file.

For details, see "[Emulating Users with Iterations](#)" on [page 938](#).

## **How to Parameterize Security Elements**

This task describes how to independently parameterize the security elements in a script.

### **1. Open the Security Scenario Editor**

Select **SOA Tools > Security Scenario Editor**.

## 2. Set up a scenario for each Vuser

Set up a scenario for each Vuser as described in "[How to Create and Manage Security Scenarios](#)" on page 940. We recommend you use the names `user1`, `user2`, and so forth, and save them in a new folder, `%script root%/WSDL/referencedConfig`.

## 3. Open the Parameter List window and create a parameter

Select **Vuser > Parameters List**. Create a new parameter, `<ServiceName>_shared_config`. Replace the `<ServiceName>` with the case-sensitive name of the service you are testing. To determine the exact name of the service, click **Manage Services** to see the list of services.

## 4. Add parameter values

In the values table, in each row add the file names of the security scenarios with their .stss extensions. You can use a relative path, relative to the script folder. Click **Add Row** to add multiple values. Close the Parameter List dialog box.

## 5. Call the parameter

- Click **Manage Services** and select the **Protocol and Security** tab. Click **Edit Data**.
- Select **Shared Scenario**. Click the Browse button and enter the parameter name, `<ServiceName>_shared_config`, in the test box.

# Set Security Properties Dialog Box

This dialog box enables you to set the security properties for your Web Service calls.

<b>To access</b>	<b>VuGen &gt; Insert &gt; New Step &gt; Web Service Set Security.</b> Click <b>OK</b> .
<b>Relevant tasks</b>	<a href="#">"How to Add Security to a Web Service Script"</a> on page 939
<b>See also</b>	<a href="#">"How to Add SAML Security"</a> on page 940
<b>Important Information</b>	If you have edited key algorithm or session algorithm values in the mmdrv.config file for an existing script, these values are replaced with the system default values.

## WS -Security Tab

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<code>&lt;Token Grid&gt;</code>	Displays a unique number, type and name of all tokens that have been added.

 <b>Add Security Token</b>	<p>Enables you to select a token type:</p> <p><b>Username and Password</b></p> <table border="1" data-bbox="556 388 1392 1220"> <thead> <tr> <th data-bbox="556 388 768 445">UI Element</th><th data-bbox="768 388 1392 445">Description</th></tr> </thead> <tbody> <tr> <td data-bbox="556 445 768 502"><b>Token Name</b></td><td data-bbox="768 445 1392 502">A meaningful name for the token.</td></tr> <tr> <td data-bbox="556 502 768 582"><b>Include nonce</b></td><td data-bbox="768 502 1392 582">If selected, an arbitrary number is used once to sign communication.</td></tr> <tr> <td data-bbox="556 582 768 639"><b>Username</b></td><td data-bbox="768 582 1392 639">Specify the username.</td></tr> <tr> <td data-bbox="556 639 768 696"><b>Password</b></td><td data-bbox="768 639 1392 696">Specify the password.</td></tr> <tr> <td data-bbox="556 696 768 952"><b>Password type</b></td><td data-bbox="768 696 1392 952">           Specify the password as one of the following:           <ul style="list-style-type: none"> <li data-bbox="768 783 1392 819">• Text</li> <li data-bbox="768 840 1392 876">• Hash</li> <li data-bbox="768 897 1392 933">• None</li> </ul> </td></tr> <tr> <td data-bbox="556 952 768 1220"><b>Timestamp format</b></td><td data-bbox="768 952 1392 1220">           Specify the timestamp format:           <ul style="list-style-type: none"> <li data-bbox="768 1030 1392 1066">• Full</li> <li data-bbox="768 1087 1392 1123">• Created</li> <li data-bbox="768 1144 1392 1180">• None</li> </ul> </td></tr> </tbody> </table> <p><b>X.509 Certificate Token</b></p> <table border="1" data-bbox="556 1284 1392 1628"> <thead> <tr> <th data-bbox="556 1284 768 1341">UI Element</th><th data-bbox="768 1284 1392 1341">Description</th></tr> </thead> <tbody> <tr> <td data-bbox="556 1341 768 1421"><b>Token Name</b></td><td data-bbox="768 1341 1392 1421">A meaningful name for the token.</td></tr> <tr> <td data-bbox="556 1421 768 1537"><b>Certificate</b></td><td data-bbox="768 1421 1392 1537">If selected, an arbitrary number is used once to sign communication.</td></tr> <tr> <td data-bbox="556 1537 768 1628"><b>Reference Type</b></td><td data-bbox="768 1537 1392 1628">Specify the username.</td></tr> </tbody> </table> <p><b>Kerberos Token</b></p>	UI Element	Description	<b>Token Name</b>	A meaningful name for the token.	<b>Include nonce</b>	If selected, an arbitrary number is used once to sign communication.	<b>Username</b>	Specify the username.	<b>Password</b>	Specify the password.	<b>Password type</b>	Specify the password as one of the following: <ul style="list-style-type: none"> <li data-bbox="768 783 1392 819">• Text</li> <li data-bbox="768 840 1392 876">• Hash</li> <li data-bbox="768 897 1392 933">• None</li> </ul>	<b>Timestamp format</b>	Specify the timestamp format: <ul style="list-style-type: none"> <li data-bbox="768 1030 1392 1066">• Full</li> <li data-bbox="768 1087 1392 1123">• Created</li> <li data-bbox="768 1144 1392 1180">• None</li> </ul>	UI Element	Description	<b>Token Name</b>	A meaningful name for the token.	<b>Certificate</b>	If selected, an arbitrary number is used once to sign communication.	<b>Reference Type</b>	Specify the username.
UI Element	Description																						
<b>Token Name</b>	A meaningful name for the token.																						
<b>Include nonce</b>	If selected, an arbitrary number is used once to sign communication.																						
<b>Username</b>	Specify the username.																						
<b>Password</b>	Specify the password.																						
<b>Password type</b>	Specify the password as one of the following: <ul style="list-style-type: none"> <li data-bbox="768 783 1392 819">• Text</li> <li data-bbox="768 840 1392 876">• Hash</li> <li data-bbox="768 897 1392 933">• None</li> </ul>																						
<b>Timestamp format</b>	Specify the timestamp format: <ul style="list-style-type: none"> <li data-bbox="768 1030 1392 1066">• Full</li> <li data-bbox="768 1087 1392 1123">• Created</li> <li data-bbox="768 1144 1392 1180">• None</li> </ul>																						
UI Element	Description																						
<b>Token Name</b>	A meaningful name for the token.																						
<b>Certificate</b>	If selected, an arbitrary number is used once to sign communication.																						
<b>Reference Type</b>	Specify the username.																						

UI Element	Description
<b>Token Name</b>	A meaningful name for the token.
<b>Host</b>	The host name of the server against which you want to authenticate. In most cases, it is the host portion of the service URL.
<b>Domain</b>	The Windows domain of the server against which you want to authenticate.

### Kerberos2 Token

UI Element	Description
<b>Token Name</b>	Specify the name of the token.
<b>Host</b>	The host name of the server against which you want to authenticate. In most cases, it is the host portion of the service URL.
<b>Domain</b>	The Windows domain of the server against which you want to authenticate.

 Add Message Signature	UI Element	Description
	<b>Signing token</b>	The token to use for signing, usually an X.509 type. Select from the list of all added tokens.
	<b>Canonicalization algorithm</b>	A URL for the algorithm to use for canonicalization. A drop-down list provides common algorithms. If you are unsure which value to use, keep the default.
	<b>Transform Algorithm</b>	A URL for the Transform algorithm to apply to the message signature. A drop down list provides common algorithms. If you are unsure which value to use, keep the default.
	<b>Inclusive namespace list</b>	A list of comma-separated prefixes to be treated as inclusive (optional).
	<b>What to sign</b>	
	The SOAP elements to sign: SOAP Body, Timestamp, and WS-Addressing.	
	<b>Xpath (optional)</b>	An XPath that specifies which parts in the message to sign. If left blank, the elements selected in the Signature options field are signed. For example, <code>//*[local-name(.) = 'Body']</code> .
	<b>Token (optional)</b>	The target token you want to sign. Select from the drop-down list of all added tokens. With most services, this field should be left empty.

 Add Message Encryption	UI Element	Description
	<b>Encrypting Token</b>	The token to use for encryption, usually an X.509 type. You can select from a list of all previously created tokens.
	<b>Encrypting Type</b>	Indicates whether to encrypt the whole destination Element or only its Content.
	<b>Key algorithm</b>	<p>The algorithm to use for the encryption of the session key: RSA15 or RSAOAEP.</p> <p><b>Note:</b> If you have edited the mmdrv.config file with a custom key algorithm value for an existing script, this value is replaced with the system default value of RSA15.</p>
	<b>Session algorithm</b>	<p>The algorithm to use for the encryption of the SOAP message. You can select from a list of common values.</p> <p><b>Note:</b> If you have edited the mmdrv.config file with a custom session algorithm value for an existing script, this value is replaced with the system default of AES128.</p>
	<b>What to encrypt</b>	
	<b>Xpath (optional)</b>	An XPath that indicates the parts of the message to encrypt. If left blank, only the SOAP body is encrypted.
	<b>Token (optional)</b>	The name of the encrypted token. A drop-down box provides a list of all added tokens. With most services, this field should be left empty.
	Delete a token definition from the grid.	
	<p><b>Up/Down.</b> Positioning tools that allow you to set the priority of the security elements.</p> <p><b>Note:</b> Make sure the security elements are positioned in order of their priority.</p>	
<b>Exclude Timestamp</b>	Removes the timestamp from the SOAP header before sending the security element to the server.	

## WS Addressing

The WS-Addressing tab indicates whether WS-Addressing is used by the service, and if so, its version number. You can also specify the IP address of the server to which you want the response to be sent.

## Security Scenario Editor Dialog Box

This dialog box enables you to define security scenarios for your script.

<b>To access</b>	<b>SOA Tools &gt; Security Scenario Editor</b>
<b>Important information</b>	You can also define scenarios for a specific service. For details, see " <a href="#">How to Create and Manage Security Scenarios</a> " on page 940.
<b>Relevant tasks</b>	<a href="#">" How to Create and Manage Security Scenarios" on page 940</a>

User interface elements are described below:

UI Element	Description
	<b>New.</b> Resets the editor for defining a new security scenario. If you made changes to the current scenario, it prompts you to save them.
	<b>Load.</b> Opens an existing shared scenario from a URL or file.
	<b>Save.</b> Saves the scenario file. If you have not saved the file at least once, it prompts you for a name.
	<b>Save as.</b> Saves the scenario file at a new location.
	<b>Help.</b> Opens the Online help for security scenarios.
	<b>Close.</b> Closes the dialog box.
	Opens the Advanced Setting dialog box for setting the encoding, reliable messaging, secure session information, and proxy configuration. For details, see " <a href="#">"Advanced Scenario Setting" on page 931</a> .
<b>Scenario type</b>	The security scenario type: No scenario or a sub-type of Core, Security, WCF, or Optimization scenarios.

## Select Certificate Dialog Box

This dialog box enables you to search and locate a certificate from a file or Windows store.

<b>To access</b>	Select a scenario that uses a certificate in one of the following ways: <ul style="list-style-type: none"> <li>Open the Security Scenario Editor: Choose <b>SOA Tools &gt; Security Scenario Editor</b>.</li> <li>In the Manage Services dialog box, select the <b>Protocol and Security</b> tab and click the <b>Edit Data</b> button.</li> </ul> Select a WCF scenario that uses a client or service certificate, such as <b>WsHttpBinding</b> or <b>Federation</b> . In the <b>Certificate</b> field, click the Browse button.
<b>Important information</b>	This only applies to security scenarios that allow you to specify client, server, or service certificates.
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>"<a href="#">How to Create and Manage Security Scenarios</a>" on page 940.</li> <li>"<a href="#">How to Create and Manage Security Scenarios</a>" on page 940.</li> </ul>


## Select Certificate from File

When you choose **File**, the dialog box shows the user interface elements described below:

UI Element	Description
	<b>Browse.</b> Allows you to locate the certificate file with a .pem, .arm, .der, or .pfx extension.
<b>File</b>	The complete path of the certificate file.
<b>Password (optional)</b>	The password required to access the certificate.

## Select Certificate from Windows Store

When you choose **Windows Store**, the dialog box shows the user interface elements described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Begins the search for the certificate.
<b>Import from</b>	The location of the certificate: <ul style="list-style-type: none"> <li><b>Windows store</b></li> <li><b>File</b></li> </ul>
<b>Store location</b>	The store location, for example <b>Current User</b> .
<b>Store name</b>	The store name, for example, <b>AuthRoot</b> .

<b>Search text</b>	The text to match in the certificate name.
<b>Password (optional)</b>	The password required to access the certificate.
<b>&lt;certificate list&gt;</b>	A list of the certificates in the Windows store sorted by Subject, Issuer, Private, Store Location, and Store Name.

## Web Services Security Examples

This section illustrates several common security scenarios.

### Authenticating with a Username Token

The following example illustrates the sending of a message level username/password token (a username token), where the user name is John and the password is 1234.

```
web_service_set_security(
    SECURITY_TOKEN, "Type=USERNAME", "LogicalName=myToken", "UserName=John",
    "Password=1234", "PasswordOptions=SendPlainText", "Add=True",
    LAST);
```

### Signing a Specific Element with an X.509 Certificate

It is possible to sign only a specific element in a message. The following example signs a specific element using an XPATH expression:

```
web_service_set_security(
    SECURITY_TOKEN, "Type=X509", "LogicalName=myCert", "StoreName=My", "IDType=SubjectName",
    "IDValue=CN=myCert", "StoreLocation=CurrentUser", "Add=True",
    MESSAGE_SIGNATURE, "UseToken=myCert", "TargetPath='/*[local-name(.)='someElement' and namespace-uri(.)='http://myNamespace']]',
    LAST);
```

### Signing with an X.509 Certificate

The following example shows a script using an X.509 certificate for a digital signature.

```
web_service_set_security(
    SECURITY_TOKEN, "Type=X509", "LogicalName=myCert", "StoreName=My", "IDType=SubjectName",
    "IDValue=CN=myCert", "StoreLocation=CurrentUser", "Add=True",
    MESSAGE_SIGNATURE, "UseToken=myCert",
    LAST);
```

**Note:** The certificate needs to be installed in the Windows certificate store. In the example above, you need to set the actual store name, store location, and subject name of your certificate.

### Encrypting with a Certificate

The following sample encrypts a message with the service's X.509 certificate.

```

web_service_set_security(
    SECURITY_TOKEN, "Type=X509", "LogicalName=serviceCert", "StoreName=My", "
IDType=SubjectName", "IDValue=CN=serviceCert", "StoreLocation=CurrentUser", "Add
=False",
    ENCRYPTED_DATA, "UseToken=serviceCert",
    LAST);

```

After you specify the details of your X.509 certificate, you can encrypt a specific XPATH in the message.

Since we want to generate a Subject Key Identifier, we set the Add value to **False**.

## Authenticating with a Username Token and Encrypting with an X.509 Certificate

The following example sends a username token to the service and encrypts it with the server's X.509 certificate:

```

web_service_set_security(
    SECURITY_TOKEN, "Type=X509", "LogicalName=serviceCert", "StoreName=My", "
IDType=SubjectName", "IDValue=CN=serviceCert", "StoreLocation=CurrentUser", "Add
=True",
    SECURITY_TOKEN, "Type=USERNAME", "LogicalName=myUser", "UserName=John", "
Password=1234", "PasswordOptions=SendPlainText", "Add=True",
    ENCRYPTED_DATA, "UseToken=serviceCert", "TargetToken=myUser",
    LAST);

```

The **UseToken** and **TargetToken** properties indicate which token to use and which to encrypt. Their values reference the **LogicalName** property of the tokens.

## Encrypting and Signing a Message

This example shows how to sign a message using a private key and then encrypt it using the service's public key.

```

web_service_set_security(
    SECURITY_TOKEN, "Type=X509", "LogicalName=myCert", "StoreName=My", "IDTyp
e=SubjectName", "IDValue=CN=myCert", "StoreLocation=CurrentUser", "Add=True",
    SECURITY_TOKEN, "Type=X509", "LogicalName=serverToken", "StoreName=My", "
IDType=SubjectName", "IDValue=CN=serverCert", "StoreLocation=CurrentUser", "Add
=False",
    MESSAGE_SIGNATURE, "UseToken=myCert",
    ENCRYPTED_DATA, "UseToken=serverCert",
    LAST);

```

## Referencing an X.509 Certificate Using a Hash

In certain cases, you may be unable to reference a certificate with a subject name. This example shows how to reference the certificate using its unique hash.

```

web_service_set_security(
    SECURITY_TOKEN, "Type=X509", "LogicalName=serviceCert", "StoreName=My", "ID
Type=Base64KeyID", "IDValue=p0l0+1iuotKLl091nhjDg5reEw0=", "StoreLocation=Cu
rrentUser", "Add=False",

```

```
    ENCRYPTED_DATA, "UseToken=serviceCert",
    LAST);
```

## Troubleshooting and Limitations - Web Services

This section describes troubleshooting and limitations for the Web Services protocol.

- The **Record default web browser** option in the Recording Wizard, is only supported for Internet Explorer.
- For large SOAP envelopes, Record and Replay snapshots are disabled.
- The Import SOAP feature is not supported for envelopes containing a single element larger than 500KB.
- Recording requests with attachments or security is not supported.
- For Axis toolkit, Web service calls that include both attachments and security are not supported.
- For .NET toolkit, SOAP version 1.2 is not supported for asynchronous calls.
- You can enter text strings up to 10 KB to encode to base 64. If your string is larger, use the Get from file option.
- VuGen supports Web Service messages over JMS message Queue, but does not support JMS Topics.
- JMS Bindings Extensions are not supported.
- All services in your script should have the same security scenario. This can be configured via the Protocols and Security tab.
- Asynchronous Web Service calls and custom user handlers are not supported for WCF.
- LoadRunner cannot replay scripts containing the **soa\_xml\_validate** function.
- When using "update service", steps that are already in the script will not display the updated properties (in the step argument view) until you close and reopen the application. After you reopen the app, step arguments are updated. If the script is open when performing "update service", then on the script view arguments, the application throws an exception.

**Workaround:** Close the script file while running "update service", or reopen the test after running "update service".

- A Web Service script might not open when you import the WDSL with the Axis toolkit.

**Workaround:** Import the WDSL with the .NET toolkit.

If there is a problem recreating the scripts, do the following:

- a. Create a new test.
- b. Import the WSDL using .NET toolkit.
- c. Go to the directory of the new script.
- d. Copy the folder "WSDL" and paste it on the directory of the old script.
- e. In the directory of the old script open the 'default.cfg' file
- f. Under [WebServices] header, instead of "Toolkit=Axis" write "Toolkit=.NET"

## Troubleshooting and Limitations - Web Services

This section describes troubleshooting and limitations for the Web Services protocol.

- The **Record default web browser** option in the Recording Wizard, is only supported for Internet Explorer.
- For large SOAP envelopes, Record and Replay snapshots are disabled.
- The Import SOAP feature is not supported for envelopes containing a single element larger than 500KB.
- Recording requests with attachments or security is not supported.
- For Axis toolkit, Web service calls that include both attachments and security are not supported.
- For .NET toolkit, SOAP version 1.2 is not supported for asynchronous calls.
- You can enter text strings up to 10 KB to encode to base 64. If your string is larger, use the Get from file option.
- VuGen supports Web Service messages over JMS message Queue, but does not support JMS Topics.
- JMS Bindings Extensions are not supported.
- All services in your script should have the same security scenario. This can be configured via the Protocols and Security tab.
- Asynchronous Web Service calls and custom user handlers are not supported for WCF.
- LoadRunner cannot replay scripts containing the **soa\_xml\_validate** function.
- When using "update service", steps that are already in the script will not display the updated properties (in the step argument view) until you close and reopen the application. After you reopen the app, step arguments are updated. If the script is open when performing "update

service", then on the script view arguments, the application throws an exception.

**Workaround:** Close the script file while running "update service", or reopen the test after running "update service".

- A Web Service script might not open when you import the WSDL with the Axis toolkit.

**Workaround:** Import the WSDL with the .NET toolkit.

If there is a problem recreating the scripts, do the following:

- Create a new test.
- Import the WSDL using .NET toolkit.
- Go to the directory of the new script.
- Copy the folder "WSDL" and paste it on the directory of the old script.
- In the directory of the old script open the 'default.cfg' file
- Under [WebServices] header, instead of "Toolkit=Axis" write "Toolkit=.NET"

## Windows Sockets Protocol

### Recording Windows Sockets - Overview


The Windows Sockets protocol supports applications which communicate over the TCP/IP protocol using a Microsoft WinSock DLL. The WinSock protocol allows you to see the actual data sent and received by the buffers.

The WinSock protocol records functions that relate to the sockets, data buffers, and the Windows Sockets environment. Using VuGen, you record your application's API calls to the Winsock.dll or Wsock32.dll. For example, you could create a script by recording the actions of a telnet application. After creating a Winsock Vuser script, you can view the recorded buffers as raw data or as a snapshot. For details, see "[Windows Sockets Data](#) on the next page" or "[Windows Sockets Snapshots - Overview](#)" on page 956.

### Translation Tables

You can display Windows Sockets data in EBCDIC format through a translation table.

A translation table allows you to specify the format for recording when using the WinSock single protocol, and for code generation when using a WinSock multi protocol. This applies to users running on mainframe machines or AS/400 servers. Both the server and client machines determine the format of the data from translation tables installed on your system. If your data is in ASCII format, it does not require translation.



The first four digits of the listbox item represent the server format. The last four digits represent the client format. In the above example, the selected translation table is 002501b5. The server format is 0025 and the client format is 01b5 indicating a transfer from the server to the client. In a transmission from the client to the server, you would select the item that reverses the formats—01b50025 indicating that the client's 01b5 format needs to be translated to the server's 0025 format.

The translation tables are located in the **ebcdic** folder under the VuGen's installation folder. If your system uses different translation tables, copy them to the **ebcdic** folder.

For details on selecting a translation table in the recording options, see the "["WinSock Node" on page 244](#).

## Windows Sockets Data

When you use VuGen to create a Windows Sockets Vuser script, your actions are recorded into the three sections of the script: **vuser\_init**, **Action**, and **vuser\_end**. In addition to the Vuser script, VuGen also creates data files:

- **snapshotdata.ws** contains the data that was transmitted or received during the recording session. VuGen's Snapshot pane displays the contents of the data file. Do not modify the contents of the **snapshotdata.ws** file.
- **data.ws** contains the data that is transmitted during the replay sessions, and is expected to be received. You can right-click any step in the Editor and then select **Show Arguments** to show the buffer content that is stored in **data.ws** for the selected step. Using the **Text View** tab of the dialog box that opens, you can edit the data that is stored for any data buffer.

Several LRS functions, such as **lrs\_receive** and **lrs\_send**, handle the actual data that is transferred between servers and clients. The data that is received or transmitted is stored in data buffers, which can be very large. In order to simplify the appearance of the Vuser script, the actual data is stored in external files—not in the C file. When a data transfer occurs, the data is copied from the external file into a temporary buffer.

The external file, **data.ws**, contains the contents of all the temporary buffers. The buffers' contents are stored as sequential records. The records are marked by identifiers indicating whether the data was sent or received, and the buffer descriptor. The LRS functions use the buffer descriptors to access the data.

The descriptors have one of the following formats:

```
recv buf index    number of bytes received
send buf index   number of bytes sent
```

The buffer index begins with 0 (zero), and all subsequent buffers are numbered sequentially (1,2,3...) regardless of whether they are send or receive buffers.

In the following example, an **lrs\_receive** function was recorded during a Vuser session:

```
lrs_receive("socket1", "buf4", LrsLastArg)
```

In this example, **lrs\_receive** handled data that was received on socket1. The data was stored in the fifth receive record(buf4)—note that the index number is zero-based. The corresponding section of the **data.ws** file shows the buffer and its contents.

```
recv buf4 39
"\xff\xfb\x01\xff\xfb\x03\xff\xfd\x01"
"\r\n"
"\r\n"
"SunOS UNIX (sunny)\r\n"
"\r"
"\x0"
"\r\n"
"\r"
"\x0"
```

For task details, see ["How to View and Modify Windows Sockets Buffers" on page 960](#).

## **Windows Sockets Snapshots - Overview**

Vuser scripts based on the Windows Sockets Vuser protocol utilize VuGen's Snapshot pane.

- For an introduction to the Snapshot pane, see ["Snapshot Pane - Overview" on page 85](#).
- For details on how to work with the Snapshot pane, see ["How to Work with Snapshots" on page 88](#).
- For details on the Snapshot pane UI, see ["Snapshot Pane" on page 126](#).

When you open a Windows Sockets Vuser script, VuGen's standard Snapshot pane functionality is available. For Windows Sockets Vuser scripts, the Snapshot pane displays snapshots of the recorded data buffers.


To display a specific buffer in the Snapshot pane:

- In the Editor, select the step that contains a reference to the required buffer.
- In the Step Navigator, double-click the step that contains a reference to the required buffer.

You can view the buffer snapshots in either **Text** view or **Hex** view.


**Note:** VuGen stores the snapshot data as read-only data. You cannot modify the contents of the snapshots. However, you can modify the buffer data that is associated with any of the steps in a Vuser script. To modify the buffer data, right-click the required step in the Editor and then select Show Arguments. The Text View tab of the dialog box that opens lets you modify the buffer data. For details, see ["How to View and Modify Windows Sockets Buffers" on page 960](#)

The **Text** view shows the buffer data as text.



The **Hex** view shows the buffer data in hexadecimal representation. The data is displayed in three columns:

- The left column shows the offset of the first character in each row.
- The middle column shows the hexadecimal value of the data.
- The right column shows the data in ASCII format.



The status bar below the buffer snapshot displays information about the buffer and the data selected in the buffer:

- **Buffer number.** The buffer number of the displayed buffer.
- **Buffer size.** The total number of bytes in the buffer.
- **Buffer type.** The type of buffer—received or sent.
- **Data.** The value of the data that is selected in the buffer, in decimal and hexadecimal formats. Both big endian and little endian sequences are displayed.
- **Offset.** The offset of the selected data from the beginning of the buffer. If you select multiple bytes, the offset displays the range of the selection.

buf5: 587 bytes(s) received	BE: 1129324658 (0x43502072)	LE: 1914720323 (0x72205043)	Selection: from 235 (0xEB) to 239 (0xEF)
-----------------------------	--------------------------------	--------------------------------	------------------------------------------

### Navigating within the Buffer Data

- To go to a specific offset within the buffer (absolute), click **Go To**. In the Go To Offset dialog box enter an offset value, and then click **Apply**.
- To jump to a location relative to the selected entry, click **Go To**. In the Go To Offset dialog box, click **Advance by**, specify the number of bytes to advance, and then click **Apply**.


## **Data Navigation Tools**

VuGen provides you with **Go To** functionality to help you to navigate through the data in the Snapshot pane. This helps you to identify and analyze a specific values in the snapshot. You can move around within the data buffer by specifying an offset. You can indicate the absolute location of the data, or a location relative to the current position of the cursor within the buffer. You can also select a range of data, by specifying the starting and end offsets. For details on the dialog box options, see "["Go To Offset Dialog Box" on page 964](#)".

## **Buffer Data Editing**

You can perform all of the standard edit operations on buffer data: copy, paste, and delete. To perform edit operations on buffer data, right-click the required step in the Editor and select **Show Arguments**. You can then perform the edit operation in the **Text View** tab of the dialog box that opens. You cannot perform any edit operations in the Binary View tab.

**Note:** You perform edit operations on buffer data only, not on Snapshot data - which is read-only.



When you copy data from a buffer, VuGen allows you to copy the data either in hexadecimal format or in decimal format. When you insert data into a buffer, VuGen allows you to specify the format of the data—single byte, 2-byte, or 4-byte.

## How to Record a Windows Sockets Script

This task describes how to set up a Windows Sockets recording and how to record the session.

- 1. Open the recording options - optional**

After creating a WinSock script, select **Record > Recording Options** and click the **WinSock** node.

- 2. Select a translation table - optional**

In the **EBCDIC section**, select a translation table. If your data is in ASCII format, select the **None** option—otherwise VuGen will convert the ASCII data. For details, see "[Translation Tables](#)" on page 954.

- 3. Exclude any non-relevant sockets - optional**

In the **Exclude Settings** section, add any non-relevant sockets to the list. You should exclude hosts and ports that do not influence the server load under test, similar to the local host and the DNS port (53), which are excluded by default.

To exclude the entries from the recording, but include them in the log, clear the **Do not include excluded sockets in log** option.

For user interface details, see the "["WinSock Node" on page 244](#)".

#### 4. Set a think time threshold - optional

Indicate a think time threshold. If VuGen detects a pause in action less than the threshold time, it will not generate a **Think Time** step/ **Ir\_think\_time** function. For details, see the "["WinSock Node" on page 244](#)".

#### 5. Record the session

Record the session and save the script.

#### 6. Parameterize the script - optional

Replace recorded values with parameters using the shortcut menu. For more information, see "["Parameters" on page 408](#)"

#### 7. Regenerate the script - optional

If you need to regenerate the script, for example if you want to include an excluded host:port, or if the translation was not correct:

- Select **Record > Regenerate Script**.
- Click the **Options** link.
- Under **General**, select **Protocols**, and then under **Active Protocols**, ensure that the **Windows Sockets** check box is selected.
- Under **Sockets**, select **Winsock**, and then modify the settings.

**Note:** Options for script regeneration are available for multi-protocol scripts only.

## How to View and Modify Windows Sockets Buffers

The following steps describe how to view, modify, and navigate through WinSock buffer data.

### Modifying buffer data

You can modify buffer data in the Show Arguments dialog box for specific **Irs** steps in a Vuser script. You can use the Show Arguments dialog box to modify buffer data for the following steps:

- lrs\_length\_receive
- lrs\_length\_send
- lrs\_receive
- lrs\_receive\_ex
- lrs\_send

For further details on these steps, see the Function Reference ([Help > Function Reference](#)).

To display the Show Arguments dialog box for any of the above steps, right-click a step in the Editor and select **Show Arguments**. A dialog box opens and displays the buffer data in the **Buffer Content** section of the dialog box.

For further details about editing buffer data in Windows Sockets steps, see "["Buffer Data Editing" on page 958](#).

Note that you cannot modify any data in the Snapshot pane

### **View and modify the data in the data.ws file**

In the Solution Explorer, double-click the **data.ws** file. The contents of the data.ws file appear in the VuGen Editor. Modify the data directly in the Editor. For details, see "["Windows Sockets Data" on page 955](#).


Note that it is possible to modify data.ws files, it is recommended that you do not modify these files.

### **View the data in the Snapshot pane**

1. Ensure that the Snapshot pane is displayed.
2. Open the Vuser script in the Editor and select a step, or double-click an entry in the Step Navigator. The associated snapshot is displayed in the Snapshot pane. You cannot edit the snapshot data.

### **Navigate within the snapshot data**

To navigate within the buffer data, display in the Snapshot pane, and then click **Go to**. The Go to Offset dialog box opens.



- To go to a specific offset within the buffer (absolute), select **Go to offset** and specify an offset value. Click **Apply**.
- To jump to a location relative to the cursor, click **Advance by** and specify the number of bytes to advance. To advance ahead, enter a positive value. To move backwards within the buffer, use a negative value. Click **Apply**.
- To select a range of data within the buffer, click **Select range from** and specify the beginning and end offsets. Click **Apply**.

## Insert data into a buffer

You can insert a numerical value into a data buffer. You can insert the data as a single, double-byte, or 4-byte value. The following steps describe how to insert a number into a data buffer.

- Copy the numerical data to be inserted to the clipboard.
- Right-click a step in the Editor and select **Show Arguments**.
- In the dialog box that opens, ensure that the **Text View** tab is displayed.
- Under **Buffer Content**, right-click at the location in the buffer where you want to insert the data, and then select **Advanced > Paste Byte** or **Advanced > Paste Short (2 bytes)** or **Advanced > Paste Long (4 bytes)**.
- Click **OK**. VuGen inserts the data into the buffer.

## Copy and paste blocks of data

You can modify the buffer data as characters, decimal numbers, or hexadecimal numbers. For details, see "["Buffer Data Editing" on page 958](#)".

Note that you can edit buffer data only when you view the step arguments - you cannot edit buffer data in the Snapshot pane.

1. Right-click a step in the Editor and select **Show Arguments**. A dialog box opens and displays the buffer data in the **Buffer Content** section of the dialog box.
2. To copy buffer data:
  - As characters, select one or more bytes and press **Ctrl+c**.
  - As a decimal number, select one or more bytes, right-click in the selection and select **Advanced > Copy As Decimal Number**.
  - As a hexadecimal number, select one or more bytes, right-click in the selection and select **Advanced > Copy As Hexadecimal Number**.
3. To paste the data:
  - As characters, press **Ctrl+V**.
  - As a single byte (assuming the size of the data on the clipboard is a single byte), right-click at the desired location in the buffer and click **Advanced > Paste Byte**.
  - In short format (2-byte), right-click at the desired location in the buffer and click **Advanced > Paste Short (2 bytes)**.
  - In long format (4-byte), right-click at the desired location in the buffer and click **Advanced > Paste Long (4 bytes)**.
4. To delete data, select the data in the Text view, right-click inside the selection and select **Delete**.

## Data Buffers

When you use VuGen to create a Windows Sockets Vuser script, VuGen creates the **data.ws** data file. This file contains the data that is transmitted, and is expected to be received, during the replay sessions. You can right-click any step in the Editor and then select **Show Arguments** to show the buffer content that is stored in **data.ws** for the selected step. Using the **Text View** tab of the dialog box that opens, you can edit the data that is stored for any data buffer.

The **data.ws** data file has the following format:

- File header
- A list of buffers and their contents

The file header includes an internal version number of the data file format. The current version is 2. If you try to access data from a data file with format version 1, VuGen issues an error.

```
;WSRData 2 1
```

An identifier precedes each record, indicating whether the data was received or sent, followed by the buffer descriptor, and the number of bytes received (for **lrs\_receive** only). The buffer descriptor contains a number identifying the buffer.

For example,

```
recv buf5 25
```

indicates that the buffer contains data that was received. The record number is 5, indicating that this receive operation was the sixth data transfer (the index is zero based), and twenty-five bytes of data were received.

If your data is in ASCII format, the descriptor is followed by the actual ASCII data that was transferred by the sockets.

If your data is in EBCDIC format, it must be translated through a look-up table. For information on setting the translation table, see the ["WinSock Node" on page 244](#). The EBCDIC whose ASCII value (after translation) is printable, is displayed as an ASCII character. If the ASCII value corresponds to a non-printable character, then VuGen displays the original EBCDIC value.

```
recv buf6 39
"\xff\xfb\x01\xff\xfb\x03\xff\xfd\x01"
"\r\n"
"SunOS UNIX (sunny)\r\n"
```

The following segment shows the header, descriptors, and data in a typical data file:

```
;WSRData 2 1
send buf0 48
"\xff\xfd\x01\xff\xfd\x03\xff\xfb\x03\xff\xfb\x18"
recv buf1 15
"\xff\xfd\x18\xff\xfd\x1f\xff\xfd"
"#
"\xff\xfd"
##
"\xff\xfd"
"$"
send buf2 24
"\xff\xfb\x18"
```

## Go To Offset Dialog Box

This dialog box allows you to go to a specific location within the recorded data.

<b>To access</b>	On the Snapshot pane toolbar, click <b>Go to</b> .
<b>Relevant tasks</b>	<a href="#">"How to View and Modify Windows Sockets Buffers" on page 960</a>

User interface elements are described below:

UI Element	Description
<b>Current offset</b>	The current offset of the cursor (read only).

<b>Go to offset</b>	Goes to a specific, absolute offset within the data.
<b>Advance by...bytes</b>	Jumps to a location relative to the cursor, by a number of bytes. Positive values indicate a forward direction. Negative values indicate a reverse direction.
<b>Select range from...to...</b>	Selects a range of data within the buffer.
<b>Apply</b>	Moves the cursor to the specified offset.

## MMS (Multimedia Messaging Service) Protocol Overview

The MMS protocol is useful for sending MMS messages between mobile devices.

MMS (Multimedia Messaging Service) is an extension of the SMS protocol. Whereas SMS messages can contain only text, MMS allows you to send and receive messages with a wide range of content to MMS capable handsets. This content can be in the form of text, sound, email messages, images, video clips, and even streaming data. It is also possible to send multimedia messages from a mobile phone to an email address.

An MMS message typically includes a collection of attachments. While SMS messages are limited to 160 bytes, an MMS message could be several MBs in size. MMS usually requires a third generation (3G) network to enable such large messages to be delivered.

To receive an MMS message, a mobile phone receives an MMS notification over SMS. The SMS message can be received over various SMS protocols such as SMPP, UCP, and CIMD2. The SMS message contains a unique path to the MMS message stored in the MMSC server's database and the mobile phone uses this path to download the message from the SMSC. The current version of VuGen supports the receiving of MMS notifications over the SMPP interface.

Multimedia Messaging Service Vuser scripts support the 1.0 and 1.1 versions of the MMS protocol, as defined by OMA (Open Mobile Alliance organization). Using MMS Vusers, you can send MMS messages to the MMSC server directly over the HTTP protocol, or over the WAP protocol through a WAP gateway.

Multimedia Messaging Service functions emulate the sending and receiving of MMS messages. Each function begins with an **mm** prefix. For detailed syntax information for these functions, see the Function Reference ([Help > Function Reference](#)).

## How to Run an MMS Scenario in the Controller

An MMS (Multimedia Messaging Service) scenario requires a command line setting.

To set the MMS command line setting:

1. From the Scenario Schedule screen, click **Details**. The Group Information dialog is displayed.
2. If the Command line box is not visible, click the **More** button.
3. Add the following to the end of the Command line text: `-usingwininet yes`
4. Click **OK** to accept the Command line switch.

# Advanced Topics

## Manually Programming a Script using the VuGen Editor

### Manually Programming Scripts - Overview

VuGen allows you to program your own functions into the script, instead of recording an actual session. You can use the Vuser API or standard programming functions. Vuser API functions allow you to gather information about Vusers. For example, you can use Vuser functions to measure server performance, control server load, add debugging code, or retrieve run-time information about the Vusers participating in the test or monitoring.

This chapter describes how to program a Vuser script from within the VuGen editor, incorporating your application's libraries or classes.

You can also develop a Vuser script through programming within the Visual C and Visual Basic environments. In these environments, you develop your Vuser script within your development application, while importing the Vuser API function libraries. For more information, see ["Creating Scripts in External IDEs" on page 969](#).

To create a customized script, you first create a skeleton script. The skeleton script contains the three primary sections of a script: **init**, **actions**, and **end**. These sections are empty and you manually insert functions into them.

You can create empty scripts for the C and Java programming languages.

### C Vuser Scripts

In a C Vuser script, you can use any C code that conforms to the standard ANSI conventions. To create an empty C Vuser script, select **C Vuser** in the Create a New Script dialog box. VuGen creates an empty C Vuser script:

```
Action1()
{
    return 0;
}
```

You can use C Vuser functions in all of Vuser script types that use C functions.

See the Function Reference ([Help > Function Reference](#)) for a C reference that includes syntax and examples of commonly used C functions.

#### Guidelines for Using C Functions

All standard ANSI-C conventions apply to C Vuser scripts, including control flow and syntax. You can add comments and conditional statements to the script just as you do in other C programs. You declare and define variables using ANSI C conventions.

The C interpreter that is used to run Vuser scripts accepts the standard ANSI C language. It does not support any Microsoft extensions to ANSI C.

Before you add any C functions to a Vuser script, note the following limitations:

- A Vuser script cannot pass the address of one of its functions as a callback to a library function.
- The **stdargs**, **longjmp**, and **alloca** functions are not supported in Vuser scripts.
- Vuser scripts do not support structure arguments or return types. Pointers to structures are supported.
- In Vuser scripts, string literals are read-only. Any attempt to write to a string literal generates an access violation.
- C Functions that do not return int, must be casted. For example,  
`extern char * strtok();`

## Calling libc Functions

In a Vuser script, you can call **libc** functions. However, since the interpreter that is used to run Vuser scripts does not support any Microsoft extensions to ANSI C, you cannot use Microsoft's include files. You can either write your own prototypes, or ask HP Customer Support to send you ANSI-compatible include files containing prototypes for **libc** functions.

## Linking Mode

The C interpreter that is used to run Vuser scripts uses a "lazy" linking mode in the sense that a function need not be defined at the start of a run, as long as the function is defined before it is used. For example:

```
lr_load_dll("mydll.dll");
    myfun(); /* defined in mydll.dll -- can be called directly,
               immediately after myfun.dll is loaded. */
```

## Java Vusers

In Java Vuser scripts, you can place any standard Java code. To create an empty Java Vuser script, select **Java Vuser** in the New Virtual User dialog box. VuGen creates an empty Java script:

```
import lrapi.lr;
public class Actions
{
    public int init() {
        return 0;
    }
    public int action() {
        return 0;
    }
    public int end() {
        return 0;
    }
}
```

```
    }  
}
```

Note that for Java type Vusers, you can only edit the **Actions** class. Within the Actions class, there are three methods: **init**, **action**, and **end**. Place initialization code in the **init** method, business processes in the **action** method, and cleanup code in the **end** method.

## .NET Vusers

You can create an empty .NET Vuser script, in which to place .NET code. This script type lets you incorporate your existing .NET application into VuGen. To create an empty .NET Vuser script, select **.NET** in the Create a New Script dialog box.

In a .NET Vuser script the default language is C#. If your script is generated from a recorded session, VuGen enables you to change the script language from C# to VB.NET by selecting Visual Basic .NET Language from **Record > Recording Options > General > Script** and regenerating the script.

**Tip:** You can edit the script in Visual Studio by clicking the  button.

The following example shows the Action section of an empty .NET script:

```
namespace Script  
{  
    public partial class VuserClass  
    {  
        public int Action()  
        {  
            // Add your code here  
            return 0;  
        }  
    }  
}
```

**Note:** Enter the business process code in the **Action** method. Add initialization code to the **vuser\_init** method, and cleanup code to the **vuser\_end** method.

## Creating Scripts in External IDEs

### Creating Vuser Scripts or LoadRunner Tests in Visual Studio or Eclipse

This chapter describes how to develop a Vuser script or LoadRunner test through programming within the Visual Studio or Eclipse environments.

LoadRunner provides add-ins that allow you to work with Visual Studio or Eclipse.

There are two types of add-ins:

- Visual Studio IDE add-in
- Visual Studio/Eclipse IDE add-in for Developers

The basic **Visual Studio IDE add-in** allows you to create a Vuser script within the Visual Studio environment. You program the script using standard LoadRunner or C# functions, within your native environment. You can then add the script to a LoadRunner scenario.

The **Visual Studio IDE add-in for Developers** allows you to create a LoadRunner test directly from within Visual Studio or Eclipse. You program the script using standard LoadRunner, C#, or Java functions, within your native environment. When you have completed the test, you can add run-time settings and replay the test. The test is saved as an NUnit (Visual Studio) or JUnit (Eclipse) test. You can add these tests to a scenario directly from the LoadRunner Controller as system or unit tests.

These add-ins are provided in the main DVD folder of the LoadRunner product, under the **Additional Components** folder. Be sure to select the correct Visual Studio add-in for your version of Visual Studio.

Once you install the basic **Visual Studio IDE add-in**, you can create a new LoadRunner script within Visual Studio.

Alternatively, you can send the script to Visual Studio or Eclipse from within VuGen. If, for example, you created a script in VuGen and realize that you need to the capabilities of your native environment, the **Open in Visual Studio**  or **Open in Eclipse**  button opens the script in the respective application. This requires you to have first installed the basic **Visual Studio IDE add-in**. (For Eclipse, LoadRunner internally installs the add-in the first time you choose **Open in Eclipse**). For details, see "[Debugging .NET Vuser Scripts](#)" on page 726 or "[Opening Java Vuser Scripts in Eclipse](#)" on page 670.

When working in Visual Studio or Eclipse, the complete LoadRunner API is available from the Object browser. For information about each of the LoadRunner API functions that you can use when programming your script, see the Function Reference (**Help > Function Reference**).

## How to Create a Vuser Script in Visual Studio

LoadRunner's add-ins let you create a Vuser script in Visual Studio in VB, C++, or C#.

**To create a Vuser script in Visual Studio:**

1. Install the IDE add-in for your version of Microsoft Visual Studio from the download/DVD **Additional Components** folder. For example Additional Components\IDE Add-Ins\MS Visual Studio .NET\LRVS2010\IDEAddInSetup.exe.
2. In Visual Studio, select the appropriate template from the Installed Templates **LoadRunner**

**VB|C++|C# .NET Vuser.** Visual Studio creates a new project with one class and a template for a Vuser, and the script file, <name>.usr. The template contains three sections, **Initialize**, **Actions**, and **Terminate**.

The following example shows a Visual C# template:

```
public int Initialize()
{
    // TO DO: Add virtual user's initialization routines
    return lr.PASS;
}
public int Actions()
{
    // TO DO: Add virtual user's business process actions
    return lr.PASS;
}
public int Terminate()
{
    // TO DO: Add virtual user's termination routines
    return lr.PASS;
}
```

3. Add code to the template, in the TODO sections.
4. Open the Object Browser (**View** menu). Expand the LoadRunner node (for example **Interop.LoadRunner**) to see the LoadRunner elements. Add the desired elements to your script, such as transactions, rendezvous points, and messages.
5. Expand the Toolbar menu, **Vuser**, and enhance your script with run-time settings and parameters. For more information, see "[General > Run Logic Node](#)" on page 350 or "[Parameter List Dialog Box](#)" on page 439.
6. Use the Vuser menu to replay the script and test its functionality.
7. Select **Vuser > Create Load Scenario**, to create a LoadRunner scenario using this .usr file.
8. You can also build the LoadRunner project as a DLL file, which will be saved in the same folder as the project. You can reference this DLL directly from a LoadRunner scenario.

## How to Create a Vuser Script in Eclipse

LoadRunner's add-ins let you create a Java Vuser script in Eclipse. You can begin in Vugen and then open Eclipse or you work from start to finish in Eclipse.

### Prerequisite

1. Make sure you have JDK 1.7 (JRE 7) on your machine. Go to [java.com](#) to check your version or download the required version. After you install it, open Eclipse and select **Window > Preferences**. Navigate to the **Java > Installed JREs** node. If **jre7** is not in the **Installed JREs**

list, click **Add** and use the wizard to add its folder (for example c:\Program Files\Java\jre7). In the Installed JREs list, click the check box by **jre7** to instruct Eclipse to use this version. Close Eclipse.

### Option 1: Create script in VuGen, and develop it further in Eclipse

1. Open VuGen and create a new Java type script.
2. Record or add steps as you normally would.
3. Click the Open in Eclipse button  on the toolbar. If this is the first time you are opening Eclipse from VuGen, a message box prompts you to enter the Eclipse location. Eclipse opens with your current script in the **Package Explorer** pane.

### Option 2: Create the script in Eclipse

1. Copy the **hp.lr.vugeneclipse42addin.jar** file from the DVD's **Additional Components\IDE Add-Ins\EclipseAddin** folder into the Eclipse **dropins** folder. Extract the files from the jar file. (Alternatively, open Eclipse at least once from within VuGen. You can then create subsequent Java scripts directly from within Eclipse without having to manually copy in the addin. To do so, follow the directions in Option 1).
2. Open Eclipse. Select **File > New > Project** and expand the **LoadRunner Script** node. You can create any of the Java protocol scripts: Java Vuser, Java Record Replay, or Java over HTTP.

### Develop the script in Eclipse

1. Expand the script's node and select the **default package > Action.java** node. Code the script as you normally would in the Eclipse editor, in the appropriate sections.
2. In the script's node in the Package Explorer, expand **Referenced Libraries > classes > Irapi** > to access the desired LoadRunner elements, such as transactions, rendezvous points, and messages.
3. Expand the **Vuser** menu (this may require you to select the parent script name in the Package Explorer) and enhance your script with run-time settings and parameters. For more information, see "[General > Run Logic Node](#)" on page 350 or "[Parameter List Dialog Box](#)" on page 439.
4. Save and run the project. Select **Vuser > Run Vuser** to test the script. Then select **Vuser > Create Load Scenario** to run it from the Controller. Note that you will not be able to open this script in VuGen once you edit it in Eclipse.

## How to Develop a Unit Test Using Visual Studio (NUnit test)

A LoadRunner developer's add-in lets you create an NUnit test in Visual Studio using VB, C++, or C#.

**To create an NUnit test in Visual Studio:**

1. Install the IDE for Dev add-in for Microsoft Visual Studio from the download/DVD **Additional Components** folder. For example DVD\Additional Components\IDE Add-Ins Dev\MS Visual Studio .NET\LRVS2010\IDEAddInDevSetup.exe.
2. In Visual Studio, select the appropriate template from the Installed Templates **LoadRunner VB|C++|C# .NET Vuser**. Visual Studio creates a new project with one class and a template for a Vuser, and the script file, <name>.usr. The template contains three sections, **Initialize**, **Actions**, and **Terminate**.

The following example shows a Visual C# template:

```
public int Initialize()
{
    // TO DO: Add virtual user's initialization routines
    return lr.PASS;
}
public int Actions()
{
    // TO DO: Add virtual user's business process actions
    return lr.PASS;
}
public int Terminate()
{
    // TO DO: Add virtual user's termination routines
    return lr.PASS;
}
```

3. Add code to the template, in the TODO sections.
4. Open the Object Browser (**View** menu). Expand the LoadRunner node (for example **Interop.LoadRunner**) to see the LoadRunner elements. Add the desired elements to your script, such as transactions, rendezvous points, and messages.
5. Expand the Toolbar menu, Vuser, and enhance your test with run-time settings and parameters. For more information, see "[General > Run Logic Node](#)" on page 350 or "[Parameter List Dialog Box](#)" on page 439.
6. Run the test to verify its functionality.
7. Build the LoadRunner project as a DLL file, which will be saved in the same folder as the project.
8. Add the DLL file as a unit test in a LoadRunner scenario.

## How to Develop a Unit Test Using Eclipse (JUnit or Selenium test)

A LoadRunner developer's add-in lets you create an JUnit test in Eclipse.

**To create a unit test in Eclipse:**

1. Make sure you have JDK 1.7 (JRE 7) on your machine. Go to [oracle.com](#) to check your version or download the required version. After you install it, open Eclipse and select **Window > Preferences**. Navigate to the **Java > Installed JREs** node. If **jre7** is not in the **Installed JREs** list, click **Add** and use the wizard to add its folder (for example c:\Program Files\Java\jre7). In the Installed JREs list, click the check box by **jre7** to instruct Eclipse to use this version.
2. Run the Eclipse Dev add-in, LREclipselDEAddInDevSetup.exe, from the Eclipse from the download/DVD folder: **Additional Components\IDE Add-Ins Dev**. After installing the Eclipse add-in, rebuild the plugin cache by running the following command line string:  
**Eclipse.exe -clean**.
3. In Eclipse, open your Selenium or JUnit test.
4. Code the test as you normally would in Eclipse.
5. Build your java classes.
6. Select **Devops Vuser > Add LoadRunner API Reference** to add the desired LoadRunner functions to your script as well as transactions, rendezvous points, and messages.
7. Expand the **Devops Vuser** menu and enhance the test with run-time settings and parameters. For more information, see "[General > Run Logic Node](#)" on page 350 or "[Parameter List Dialog Box](#)" on page 439.
8. Select **Devops Vuser > Run Vuser** to run the test from within Eclipse to verify its functionality.
9. Use the **Devops Vuser** menu to launch the LoadRunner Controller, or add the test to a Controller scenario that is already open.
10. Add the class file at any time as a unit test, to a LoadRunner scenario. For details, see "[New Scenario Dialog Box](#)" on page 1061.

## Using DLLs and Customizing VuGen

### Calling Functions from External DLLs

You can call functions that are defined in external DLLs. By calling external functions from your script, you can reduce the memory footprint of your script and the overall run-time.

To call the external function, you load the DLL in which the function is defined.

You can load a DLL in one of the following ways:

- Locally (for one script) by using the **Ir\_load\_dll** function. For task details, see "[How to Load a DLL Locally](#)" on the next page.

- Globally (for all scripts) by adding statements to the **vugen.dat** file. For task details, see "[How to Load a DLL Globally](#)" on the next page.

## How to Load a DLL Locally

This task describes how to use the **lr\_load\_dll** function to load a DLL into your Vuser script. Once the DLL is loaded, you can call any function defined within the DLL without having to declare it in your script.

### Call a function defined in a DLL

1. In a C Vuser script, add an **lr\_load\_dll** function to load the DLL at the beginning of your script. Place the statement at the beginning of the **vuser\_init** section. **lr\_load\_dll** replaces the **ci\_load\_dll** function.

Use the following syntax:

```
lr_load_dll( library_name);
```

Note that for Linux platforms, DLLs are known as shared libraries. The extension of the libraries is platform dependent.

2. Call the function defined in the DLL in the appropriate place within your script.

In the following example, the **insert\_vals** function, defined in **orac1.dll**, is called, after the creation of the **Test\_1** table.

```
int LR FUNC Actions(LR PARAM p)
{
    lr_load_dll("orac1.dll");

    lrd_stmt(Csr1, "create table Test_1 (name char(15), id integer)\n", -1,
              1 /*Deferred*/, 1 /*Dflt Ora Ver*/, 0);
    lrd_exec(Csr1, 0, 0, 0, 0, 0);
    /* Call the insert_vals function to insert values into the table. */
    insert_vals();
    lrd_stmt(Csr1, "select * from Test_1\n", -1, 1 /*Deferred*/, 1 /*Dflt Ora Ve
r*/, 0);
    lrd_bind_col(Csr1, 1, =;NAME_D11, 0, 0);
    lrd_bind_col(Csr1, 2, =;ID_D12, 0, 0);
    lrd_exec(Csr1, 0, 0, 0, 0, 0);
    lrd_fetch(Csr1, -4, 15, 0, PrintRow14, 0);
    ...
}
```

**Note:** You can specify a full path for the DLL. If you do not specify a path, **lr\_load\_library** searches for the DLL using the standard sequence used by the C++ function, **LoadLibrary** on Windows platforms. On Linux platforms you can set the **LD\_LIBRARY\_PATH** environment variable (or the platform equivalent). The **lr\_load\_dll** function uses the same search rules as **dlopen**. For more information, see the main pages for **dlopen** or its

equivalent.

## How to Load a DLL Globally

This task describes how to load a DLL globally, to make its functions available to all your Vuser scripts. Once the DLL is loaded, you can call any function defined within the DLL, without having to declare it in your script.

### Load a DLL Globally

1. Add a list of the DLLs you want to load to the appropriate section of the *mdrv.dat* file, located in your application's *dat* folder.

Use the following syntax:

```
PLATFORM_DLLS=my_dll1.dll, my_dll2.dll, ...
```

replacing the word *PLATFORM* with your specific platform. For a list of platforms, see the beginning section of the *mdrv.dat* file.

For example, to load DLLs for Winsock Vusers on an NT platform, add the following statement to the *mdrv.dat* file:

```
[WinSock]
ExtPriorityType=protocol
WINNT_EXT_LIBS=wsrun32.dll
WIN95_EXT_LIBS=wsrun32.dll
LINUX_EXT_LIBS=liblrs.so
SOLARIS_EXT_LIBS=liblrs.so
HPUX_EXT_LIBS=liblrs.sl
AIX_EXT_LIBS=liblrs.so
LibCfgFunc=winsock_exten_conf
UtilityExt=lrun_api
ExtMessageQueue=0
ExtCmdLineOverwrite=-WinInet No
ExtCmdLineConc=-UsingWinInet No
WINNT_DLLS=user_dll1 .dll, user_dll2 .dll, ...
```

2. Call the function defined in the DLL in the appropriate place within your script.

## Recording OLE Servers

VuGen currently does not support recording for OLE applications. These are applications where the actual process is not launched by the standard process creation routines, but by the OLE Automation system. However, you can create a Vuser script for OLE applications based on the following guidelines.

There are two types of OLE servers: executables, and DLLs.

## DLL Servers

If the server is the DLL, it will eventually be loaded into the application process space, and VuGen will record the call to LoadLibrary. In this case, you may not even realize that it was an OLE application.

## Executable Servers

If the server is the executable, you must invoke the executable in the VuGen in a special way:

- First, determine which process actually needs to be recorded. In most cases, the customer knows the name of the application's executable. If the customer doesn't know the name of the application, invoke it and determine its name from the NT Task Manager.
- After you identify the required process, click **Start Recording** in VuGen. When prompted for the Application name, enter the OLE application followed by the flag "/Automation". Next, launch the user process in the usual way (not via VuGen). VuGen records the running OLE server and does not invoke another copy of it. In most cases, these steps are sufficient to enable VuGen to record the actions of an OLE server.
- If you still are experiencing difficulties with recording, you can use the CmdLine program to determine the full command line of a process which is not directly launched. (The program is available in a knowledge base article on the Customer Support Web site, <http://support.hp.com>)

## Using CmdLine

In the following example, CmdLine.exe is used to determine the full command line for the process MyOleSrv.exe, which is launched by some other process.

### Determine its full command line

1. Rename *MyOleSrv.exe* to *MyOleSrv.orig.exe*.
2. Place *CmdLine.exe* in the same folder as the application, and rename it to *MyOleSrv.exe*.
3. Launch *MyOleSrv.exe*. It issues a popup with a message containing the complete command line of the original application, (including additional information), and writes the information into *c:\temp\CmdLine.txt*.
4. Restore the old names, and launch the OLE server, *MyOleSrv.exe*, from VuGen with the correct command line parameters. Launch the user application in a regular way - not through VuGen. In most cases, VuGen will record properly.

### If you still are experiencing difficulties with recording, proceed with the following steps:

1. Rename the OLE server to *MyOleSrv.1.exe*, and *CmdLine* to *MyOleSrv.exe*.
2. Set the environment variables "CmdStartNotepad" and "CmdNoPopup" to 1. See "[CmdLine Environment Variables](#)" on the next page for a list of the CmdLine environment variables.

3. Start the application (not from VuGen). Notepad opens with the full command line. Check the command line arguments. Start the application several times and compare the command line arguments. If the arguments are the same each time you invoke the application, then you can reset the CmdStartNotepad environment variable. Otherwise, leave it set to "1".
4. In VuGen, invoke the program, MyOleSrv.1.exe with the command line parameters (use Copy/Paste from the Notepad window).
5. Start the application (not from within VuGen).

## ***CmdLine Environment Variables***

You can control the execution of CmdLine through the following environment variables:

<b>CmdNoPopup</b>	If set, the popup window will not appear.
<b>CmdOutFileName</b>	If set, and non-empty, CmdLine will attempt to create this file instead of c:\temp\CmdLine.txt.
<b>CmdStartNotepad</b>	If set, the output file will be displayed in the notepad (Best used with CmdNoPopup).

## **How to Create a New Vuser Type**

The following steps describe how to create a new Vuser type.

### **1. Edit the mdrv.dat file**

Edit the mdrv.dat file which resides in the M\_LROOT\dat folder. Add a section for the new Vuser type with all of the applicable parameters from the following list.

```
[<extension_name>]
ExtPriorityType=< {internal, protocol}>
WINNT_EXT_LIBS=<dll name for NT>
WIN95_EXT_LIBS=<dll name for 95>
SOLARIS_EXT_LIBS=<dll name for Solaris>
LINUX_EXT_LIBS=<dll name for Linux>
HPUX_EXT_LIBS=<dll name for HP>
AIX_EXT_LIBS=<dll name for IBM>
LibCfgFunc=<configuration function name>
UtilityExt=<other extensions list>
WINNT_DLLS=<dlls to load to the interpreter context, for NT>
WIN95_DLLS=<dlls to load to the interpreter context, for 95>
SOLARIS_DLLS=<dlls to load to the interpreter context, for Solaris>
LINUX_DLLS=<dlls to load to the interpreter context, for Linux>
```

```
HPUX_DLLS=<dlls to load to the interpreter context, for HP>
AIX_DLLS=<dlls to load to the interpreter context, for IBM>
ExtIncludeFiles=<extra include files. several files can be separated by a comma>
ExtCmdLineConc=<extra command line (if the attr exists concatenate value)>
ExtCmdLineOverwrite=<extra command line (if the attr exists overwrite value)>
CallActionByNameFunc=<interpreter exec_action function>
GetFuncAddress=<interpreter get_location function>
RunLogicInitFunc=<action_logic init function>
RunLogicRunFunc=<action_logic run function>
RunLogicEndFunc=<action_logic end function>
```

For example, an Oracle NCA Vuser type is represented by:

```
[Oracle_NCA]
ExtPriorityType=protocol
WINNT_EXT_LIBS=ncarp11i.dll
WIN95_EXT_LIBS=ncarp11i.dll
LINUX_EXT_LIBS=liboranca11i.so
SOLARIS_EXT_LIBS=liboranca11i.so
HPUX_EXT_LIBS=liboranca11i.sl
AIX_EXT_LIBS=liboranca11i.so
LibCfgFunc=oracle_gui_configure
UtilityExt=lrun_api,HttpEngine
ExtCmdLineOverwrite=-WinInet No
ExtCmdLineConc=-UsingWinInet No
SecurityRequirementsFiles=oracle_nca.asl
SecurityMode=On
```

VuGen was designed to be able to handle a new Vuser type with no code modifications. You may, however, need to add a special View.

There is no generic driver supplied with VuGen, but you can customize one of the existing drivers. To use a customized driver, modify *mdrv.dat*. Add a line with the platform and existing driver, then add a new line with your customized driver name, in the format <platform>\_DLLS=<my\_replay.dll name>. For example, if your SAP replay dll is called SAPPLAY32.DLL, add the following two lines to the [sap] section of *mdrv.dat*:

```
WINNT=sapdrv32.exe
WINNT_DLLS=sapplay32.dll
```

## 2. Add a CFG file (optional)

You can specify a configuration file to set the default run-time settings for your protocol. You define it in the LibCfgFunc variable in the *mdrv.dat* file, or place one called *default.cfg* in the new protocols subfolder under templates. A sample *default.cfg* follows.

```
[ThinkTime]
Options=NOTHINK
```

```
Factor=1
LimitFlag=0
Limit=1
[Iterations]
NumOfIterations=1
IterationPace=IterationASAP
StartEvery=60
RandomMin=60
RandomMax=90
[Log]
LogOptions=LogExtended
MsgClassData=0
MsgClassParameters=0
MsgClassFull=1
```

### 3. Insert an LRP file

In the dat/protocols folder, insert an *l/p* file which defines the protocol. This file contains the configuration information for the protocol in the Protocol, Template, VuGen, and API sections. Certain protocols may have additional sections, corresponding to the additional run-time setting options.

The Protocol section contains the name, category, description, and bitmap location for the protocol.

```
[Protocol]
Name=WAP
CommonName=WAP
Category=Wireless
Description=Wireless Application Protocol - used for Web-based, wireless communication between mobile devices and content providers.
Icon=bitmaps\wap.bmp
Hidden=0
Single=1
Multi=0
```

The Template section indicates the name of the various sections of the script and the default test name.

```
[Template]
vuser_init.c=init.c
vuser_end.c=end.c
Action1.c=action.c
Default.usp=test.usp
@{@TestName@}@.usr=wap.usr
default.cfg=default.cfg
```

The **VuGen** section has information about the record and replay engines, along with the necessary DLLs and run-time files.

The **API** section contains information about the protocol's script API functions.

You can use one of the existing *lrp* files in the protocols folder as a base for your new protocol.

#### 4. Specify a Template

After adding an *lrp* file, insert a subfolder to *M\_LROOT\template* with a name corresponding to the protocol name defined in the *lrp* file. In this subfolder, insert a *default.cfg* file which defines the default settings for the general and run-time settings.

If you want to use a global header file for all of your protocol's scripts, add a file named *globals.h*. This file should contain an include statement which points to a header file for the new protocol. For example, the template/http subfolder contains a file called *globals.h* which directs VuGen to the *as\_web.h* file in the include folder:

```
#include #as_web.h"
```

## VuGen File and Library Locations

The VuGen .dat files contain the location information of the script's files, as well as the library files for specific protocols.

There are two .dat files used by VuGen: **vugen.dat** and **mdrv.dat**.

### vugen.dat

This *vugen.dat* file resides in the *M\_LROOT\dat* folder and contains general information about VuGen, to be used by both the VuGen and the Controller.

```
[Templates]
RelativeDirectory=template
```

The Templates section indicates where the templates are for the VuGen protocols. The default entry indicates that they are in the relative *template* folder. Each protocol has a subfolder under *template*, which contains the template files for that protocol.

The next section is the **GlobalFiles** section.

```
[GlobalFiles]
main.c=main.c
@@TestName@@.usr=test.usr
default.cfg=test.cfg
default.usp=test.usp
```

The GlobalFiles section contains a list of files that VuGen copies to the test folder whenever you create a new test. For example, if you have a test called "user1", then VuGen will copy main.c, user1.usr and user1.cfg to the test folder.

The ActionFiles section contains the name of the file containing the Actions to be performed by the Vuser and upon which to perform iterations.

```
[ActionFiles]
@@actionFile@@=action.c
```

In addition to the settings shown above, *vugen.dat* contains settings that indicate the operating system and other compilation related settings.

### **mdrv.dat**

The mdrv.dat file contains a separate section for each protocol defining the location of the library files and driver executables. For information about how to use this file to create a new protocol, see "[How to Create a New Vuser Type](#)" on page 978.

## **Storing Run-Time Settings in External Files**

Vuser behavior refers to the items that you can set in the run-time settings, such as wait times, pacing times, looping iterations, and logging.

Since VuGen creates the Vuser script and the Vuser behavior as two independent sources, you can configure user behavior without directly referencing the Vuser script. This feature lets you make configuration changes to a Vuser and store several 'profiles' for the same Vuser script.

VuGen stores the behavior settings in the default **Vuser.cfg** file. You can save several versions of this file for different user behavior and then run the Vuser script referencing the relevant .cfg file.

By default, you cannot control the behavior file from VuGen. VuGen automatically uses the .cfg file with the same name as the script.

To call a specific configuration file, run the Vuser from the command line adding the following string:

```
-cfg c:\tmp\<MyCustomConfigFile>.cfg
```

For information on command line parameters, see [Command Line Parameters](#).

**Note:** The Linux utility, *run\_db\_vuser*, does not support this option.

## **Creating and Running Scripts in Linux**

### **Creating and Running Scripts in Linux - Overview**

You can use VuGen on a Linux environment in the following ways:

- You can use VuGen to create Vuser scripts that run on Linux platforms. You record your application in a Windows environment and run it in Linux—recording is not supported on Linux.
- Users working in Linux-only environments can program Vuser scripts. Scripts can be programmed in C or C++ and they must be compiled into a dynamic library.

To create a script through programming, you can use a Vuser template as a basis for a larger Vuser scripts. The template provides:

- correct program structure

- Vuser API calls
- source code and makefiles for creating a dynamic library

## Programming Vuser Actions

The Vuser script files, *test.c*, *test.usr*, and *test.cfg*, can be customized for your Vuser.

You program the actual Vuser actions into the *test.c* file. This file has the required structure for a programmed Vuser script. The Vuser script contains three sections: *vuser\_init*, *Actions*, and *vuser\_end*.

Note that the template defines extern C for users of C++. This definition is required for all C++ users, to make sure that none of the exported functions are modified inadvertently.

```
#include "lrun.h"
#if defined(__cplusplus) || defined(cplusplus) extern "C"
{
#endif
int LR_FUNC vuser_init(LR_PARAM p)
{
    lr_message("vuser_init done\n");

    return 0;
}
int Actions(LR_PARAM p)
{
    lr_message("Actions done\n");

    return 0;
}
int vuser_end(LR_PARAM p)
{
    lr_message("vuser_end done\n");

    return 0;
}
#endif
```

You program Vuser actions directly into the empty script, before the **lr\_message** function of each section.

The *vuser\_init* section is executed first, during initialization. In this section, include the connection information and the logon procedure. The *vuser\_init* section is only performed once each time you run the script.

The *Actions* section is executed after the initialization. In this section, include the actual operations performed by the Vuser. You can set up the Vuser to repeat the *Actions* section (in the *test.cfg* file).

The *vuser\_end* section is executed last, after all of the Vuser's actions. In this section, include the clean-up and logoff procedures. The *vuser\_end* section is only performed once each time you run the script.

**Note:** LoadRunner controls Vusers by sending SIGHUP, SIGUSR1, and SIGUSR2 Linux signals. Do not use these signals in your Vuser programs.

## How to Create a Template

VuGen includes a utility that copies a template into your working folder. The utility is called `mkdbtest`, and is located in `$M_LROOT/bin`. You run the utility by typing:


```
mkdbtest name
```

When you run `mkdbtest`, it creates a folder called `name`, which contains the template file, `name.c`. For example, if you type:

```
mkdbtest test1
```

`mkdbtest` creates a folder called `test1`, which contains the template script, `test1.c`.

When you run the `mkdbtest` utility, a folder is created containing four files `test.c`, `test.usr`, `test.cfg` and `Makefile`, where `test` is the test name you specified for `mkdbtest`.



## How to Configure Run-Time Settings Manually

To configure Vuser run-time settings, you modify the `default.cfg` and `default.usp` files created with the script. These run-time settings correspond to VuGen's run-time settings. (See ["Run-Time Settings" on page 317](#).) The `default.cfg` file contains the setting for the General, Think Time, and Log options. The `default.usp` file contains the setting for the Run Logic and Pacing.

### General Options

There is one General option for Linux Vuser scripts:

**ContinueOnError** instructs the Vuser to continue when an error occurs. To activate the option, specify 1. To disable the option, specify 0.

In the following example, the Vuser will continue on an error.

```
[General]
ContinueOnError=1
```

### Think Time Options

You can set the think time options to control how the Vuser uses think time during script execution.

You set the parameters Options, Factor, LimitFlag, and Limit parameters according to the following chart.

Option	Options	Factor	LimitFlag	Limit
Ignore think time	NOTHINK	N/A	N/A	N/A
Use recorded think time	RECORDED	1.000	N/A	N/A
Multiply the recorded think time by...	MULTIPLY	number	N/A	N/A
Use random percentage of recorded think time	RANDOM	range	lowest percentage	upper percentage
Limit the recorded think time to...	RECORDED/MULTIPLY	number (for MULTIPLY)	1	value in seconds

To limit the think time used during execution, set the LimitFlag variable to 1 and specify the think time Limit, in seconds.

In the following example, the settings tell the Vuser to multiply the recorded think time by a random percentage, ranging from 50 to 150.

```
[ThinkTime]
Options=RANDOM
Factor=1
LimitFlag=0
Limit=0
ThinkTimeRandomLow=50
ThinkTimeRandomHigh=150
```

## Log Options

You can set the log options to create a brief or detailed log file for the script's execution.

```
[Log]
LogOptions=LogBrief
MsgClassData=0
MsgClassParameters=0
MsgClassFull=0
```

You set the parameters LogOptions, MsGClassData, MsgClassParameters, and MsgClassFull variables according to the following chart:

Logging Type	LogOptions	MsgClassData	MsgClassParameters	MsgClassFull
Disable Logging	LogDisabled	N/A	N/A	N/A
Standard Log	LogBrief	N/A	N/A	N/A

Parameter Substitution (only)	LogExtended	0	1	0
Data Returned by Server (only)	LogExtended	1	0	0
Advanced Trace (only)	LogExtended	0	0	1
All	LogExtended	1	1	1

In the following example, the settings tell the Vuser to log all data returned by the server and the parameters used for substitution.

```
[Log]
LogOptions=LogExtended
MsgClassData=1
MsgClassParameters=1
MsgClassFull=0
```

## Iterations and Run Logic

You can set the Iteration options to perform multiple iterations and control the pacing between the iterations. You can also manually set the order of the actions and their weight. To modify the run logic and iteration properties of a script, you must edit the *default.usp* file.

To instruct the Vuser to perform multiple iterations of the Actions section, set *RunLogicNumOfIterations* to the appropriate value.

To control the pacing between the iterations, set the *RunLogicPaceType* variable and its related values, according to the following chart:

Pacing	RunLogicPaceType	Related Variables
As soon as possible	ASAP	N/A
Wait between Iterations for a set time	Const	RunLogicPaceConstTime
Wait between iterations a random time	Random	RunLogicRandomPaceMin, RunLogicRandomPaceMax
Wait after each iteration a set time	ConstAfter	RunLogicPaceConstAfterTime
Wait after each iteration a random time	After	RunLogicAfterPaceMin, RunLogicAfterPaceMax

In the following example, the settings tell the Vuser to perform four iterations, while waiting a random number of seconds between iterations. The range of the random number is from 60 to 90 seconds.

```
[RunLogicRunRoot]
MercIniTreeFather=""
MercIniTreeSectionName="RunLogicRunRoot"
RunLogicRunMode="Random"
RunLogicActionOrder="Action,Action2,Action3"
RunLogicPaceType="Random"
RunLogicRandomPaceMax="90.000"
RunLogicPaceConstTime="40.000"
RunLogicObjectKind="Group"
RunLogicAfterPaceMin="50.000"
Name="Run"
RunLogicNumOfIterations="4"
RunLogicActionType="VuserRun"
RunLogicAfterPaceMax="70.000"
RunLogicRandomPaceMin="60.000"
MercIniTreeSons="Action,Action2,Action3"
RunLogicPaceConstAfterTime="30.000"
```

## How to Define Transaction and Insert Rendezvous Points Manually

When programming a Vuser script without VuGen, you must manually configure the Vuser file in order to enable transactions and rendezvous. The configuration settings are listed in the test.usr file.

```
[General]
Type=any
DefaultCfg=Test.cfg
BinVuser=libtest.libsuffix
RunType=Binary
[Actions]
vuser_init=
Actions=
vuser_end=
[Transactions]
transaction1=
[Rendezvous]
Meeting=
```

Each transaction and rendezvous must be defined in the *usr* file. Add the transaction name to the Transactions section (followed by an "="). Add each rendezvous name to the Rendezvous section (followed by an "="). If the sections are not present, add them to the *usr* file as shown above.

## How to Compile Scripts Manually on Linux

After you modify the template, you compile it with the appropriate *Makefile* in the script's folder. The compiler creates a dynamic library called **libtest.so**.

You can modify the *Makefile* and assign additional compiler flags and libraries by modifying the appropriate sections.

If you are working with a general template, you must include your application's libraries and header files. For example, if your application uses a library called *test/lib*, include it in the LIBS section.

```
LIBS      = \
    -Ltestlib \
    -Llrun50 \
    -lm
```

After you modify the *Makefile*, type `make` from the command line in the working folder to create the dynamic library files for the Vuser script.

After you create a script, you check its functionality from the command line. Check that your script communicates with the server and performs all the required tasks. For details, see Running a Vuser from the Linux Command Line.

## Programming with the XML API

### Programming with the XML API - Overview

VuGen's support for XML allows you to dynamically work with XML code and retrieve the values during test execution. Follow these steps in creating an effective XML script:

- Record a script in the desired protocol, usually Web, Web Services, or Wireless.
- Copy the XML structures into your script.
- Add XML functions from the LR API in order to retrieve dynamic data and the XML element values.

The LR API uses XPath, the XML Path language to manipulate the text in an XML document.

You can instruct VuGen to display the output values of XML elements in the Execution log window using the run-time settings. VuGen displays the line numbers, the number of matches, and the value. To allow the displaying of values, you need to enable parameter substitution. In the run-time settings, open the **General:Log** node, select **Extended Log**, and select **Parameter Substitution**. For more information, see "["Run-Time Settings" on page 317](#)".

All Vuser API XML functions return the number of matches successfully found, or zero for failure.

## Using XML Functions

This section provides examples of how to work with data in an XML tree. Certain functions allow you to retrieve information, and others let you write information to an XML tree. The examples use the following XML tree containing the names and extensions of several employees in the Acme organization.

```
<acme_org>
  <accounting_dept>
    <employee type='PT'>
      <name>John Smith</name>
```

```
<extension>2145</extension>
</employee>
</accounting_dept>
<engineering_dept>
    <employee type='PT'>
        <name>Sue Jones</name>
        <extension>2375</extension>
    </employee>
</engineering_dept>
</acme_org>
```

## Reading Information from an XML Tree

The functions which read information from an XML tree are:

<b>lr_xml_extract</b>	Extracts XML string fragments from an XML string.
<b>lr_xml_find</b>	Performs a query on an XML string.
<b>lr_xml_get_values</b>	Retrieves values of XML elements found by a query.

To retrieve a specific value through a query, you specify the tags of the parent and child nodes in a path format.

For example, to retrieve an employee name in the Accounting department, use the following string:

```
lr_xml_get_values("XML={XML_Input_Param}",
"ValueParam=OutputParam",
"Query=/acme_org/accounting_dept/employee/name",
LAST);
```

The Execution log window (with Extended logging enabled) shows the output of this function:

Output:

```
Action.c(20): "lr_xml_get_values" was successful, 1 match processed
Action.c(25): Query result = John Smith
```

## Writing to an XML Structure

The functions which write values to an XML tree are:

<b>lr_xml_delete</b>	Deletes fragments from an XML string.
<b>lr_xml_insert</b>	Inserts a new XML fragment into an XML string.
<b>lr_xml_replace</b>	Replaces fragments of an XML string.

<b>lr_xml_set_values</b>	Sets the values of XML elements found by a query.
<b>lr_xml_transform</b>	Applies Extensible Stylesheet Language (XSL) transformation to XML data.

The most common *writing* function is **lr\_xml\_set\_values** which sets the values of specified elements in an XML string. The following example uses **lr\_xml\_set\_values** to change the phone extensions of two *employee* elements in an XML string.

First, we save the XML string to a parameter called *XML\_Input\_Param*. We want two values to be matched and substituted, so we prepare two new parameters, *ExtensionParam\_1* and *ExtensionParam\_2*, and set their values to two new phone extensions, 1111 and 2222.

**lr\_xml\_set\_values** contains the argument "ValueName=ExtensionParam", which picks up the values of *ExtensionParam\_1* and *ExtensionParam\_2*. The current extensions of the two employees are substituted with the values of these parameters, 1111 and 2222. The value of *OutputParam* is then evaluated proving that the new phone extensions were in fact substituted.

```
Action() {

    int i, NumOfValues;
    char buf[64];

    lr_save_string(xml_input, "XML_Input_Param"); // Save input as parameter
    lr_save_string("1111", "ExtensionParam_1");
    lr_save_string("2222", "ExtensionParam_2");

    lr_xml_set_values("XML={XML_Input_Param}",
                      "ResultParam=NewXmlParam", "ValueParam=ExtensionParam",
                      "SelectAll=yes", "Query=/extension", LAST);

    NumOfValues= lr_xml_get_values("XML={NewXmlParam}",
                                   "ValueParam=OutputParam", "Query=/extension",
                                   "SelectAll=yes", LAST);

    for (i = 0; i < NumOfValues; i++) /* Print the multiple values of MultiParam */
    {
        sprintf(buf, "Retrieved value %d : {OutputParam_%d}", i+1, i+1);
        lr_output_message(lr_eval_string(buf));
    }

    return 0;
}

Output:
Action.c(40): Retrieved value 1: 1111
Action.c(40): Retrieved value 2: 2222
```

# Specifying XML Function Parameters

Most XML API functions require that you specify the **XML element** and a **query**. You can also indicate if you want to retrieve all results or a single one.

## Defining the XML Element

For defining the XML element to query, you can specify a literal string of the XML element, or a parameter that contains the XML. The following example shows the XML input string defined as a literal string:

```
"XML=<employee>JohnSmith</employee>"
```

Alternatively, the **XML** string can be a parameter containing the XML data. For example:

```
"XML={EmployeeNameParam}"
```

## Querying an XML Tree

Suppose you want to find a value within an XML tag, for example, an employee's extension. You formulate a query for the desired value. The query indicates the location of the element and which element you want to retrieve or set. The path that you specify limits the scope of the search to a specific tag. You can also search for all elements of a specific type under all nodes below the root.

For a specific path, use "*Query=/full\_xml\_path\_name/element\_name*"

For the same element name under all nodes, use "*Query//element\_name*"

In the VuGen implementation of XML functions, the scope of a query is the entire XML tree. The tree information is sent to the Vuser API functions as the value of the *xml* argument.

## Multiple Query Matching

When you perform a query on an XML element, by default VuGen returns only the first match. To retrieve multiple values from a query, you specify the "SelectAll=yes" attribute within your functions. VuGen adds a suffix of *\_index* to indicate multiple parameters. For example, if you defined a parameter by the name *EmployeeName*, VuGen creates *EmployeeName\_1*, *EmployeeName\_2*, *EmployeeName\_3*, and so on.

```
lr_xml_set_values("XML={XML_Input_Param}",  
"ResultParam=NewXmlParam", "ValueParam=ExtensionParam",  
"SelectAll=yes", "Query//extension", LAST);
```

With functions that *write* to a parameter, the values written to the parameter can then be evaluated. For example, the following code retrieves and prints multiple matches of a query:

```
NumOfValues = lr_xml_get_values("Xml={XmlParam}", "Query//name",  
"SelectAll=yes", "ValueParam=EmployeeName", LAST);
```

For functions that *read* from parameters, the values of the parameters must be pre-defined. The parameter must also use the convention *ParamName\_IndexNumber*, for example *Param\_1*, *Param\_2*, *Param\_3*, and so on. This collection of parameters is also known as a parameter set.

In the following example, *lr\_xml\_set\_values* reads values from the parameter set and then uses those values in the XPath query. The parameter set that represents the employee extensions, is

called ExtensionParam. It has two members: ExtensionParam\_1 and ExtensionParam\_2. The **lr\_xml\_set\_values** function queries the XML input string and sets the value of the first match to 1111 and the second match to 2222.

```
lr_save_string("1111", "ExtensionParam_1");
lr_save_string("2222", "ExtensionParam_2");

lr_xml_set_values("XML={XML_Input_Param}",
    "ResultParam=NewXmlParam", "ValueParam=ExtensionParam",
    "SelectAll=yes", "Query=/extension", LAST);
```

## XML Attributes

VuGen contains support for attributes. You can use a simple expression to manipulate attributes of XML elements and nodes, just as you can manipulate the elements themselves. You can modify the desired attribute or only attributes with specific values.

In the following example, **lr\_xml\_delete** deletes the first cubicle element with the name attribute.

```
lr_xml_delete(      "Xml={ParamXml}",
                    "Query=/cubicle/@name",
                    "ResultParam=Result",
                    LAST
                );
```

In the next example, **lr\_xml\_delete** deletes the first cubicle element with a name attribute that is equal to Paul.

```
lr_xml_delete(      "Xml={ParamXml}",
                    "Query=/cubicle/@name='Paul'",
                    "ResultParam=Result",
                    LAST
                );
```

## Structuring XML Scripts

Initially, you create a new script in your preferred protocol. You can record a session in that protocol, or you may program the entire script without recording. Structure the Actions section of the script as follows:

- XML input declaration
- The Actions section

The XML input section contains the XML tree that you want to use as an input variable. You define the XML tree as a char type variable. For example:

```
char *xml_input=
"<acme_org>
  <employee>
    <name>John Smith</name>
    <cubicle>227</cubicle>"
```

```
    "<extension>2145</extension>"  
  "</employee>"  
  "<employee>"  
    "<name>Sue Jones</name>"  
    "<cubicle>227</cubicle>"  
    "<extension>2375</extension>"  
  "</employee>"  
</acme_org>;
```

The Action section contains the evaluation of the variables and queries for the element values. In the following example, the XML input string is evaluated using **lr\_save\_string**. The input variable is queried for employee names and extensions.

```
Action() {  
  
    /* Save the input as a parameter.*/  
    lr_save_string(xml_input, "XML_Input_Param");  
    /* Query 1 - Retrieve an employee name from the specified element.*/  
    lr_xml_get_values("XML={XML_Input_Param}",  
                      "ValueParam=OutputParam",  
                      "Query=/acme_org/employee/name", LAST);  
  
    /* Query 2 - Retrieve an extension under any path below the root.*/  
    lr_xml_get_values("XML={XML_Input_Param}",  
                      "ValueParam=OutputParam",  
                      "Query//extension", LAST);  
  
    return 0;  
}
```

## Enhancing a Recorded Session with XML

You can prepare an XML script by recording a session and then manually adding the relevant XML and Vuser API functions.

The following example illustrates how a recorded session was enhanced with Vuser API functions. Note that the only function that was recorded was **web\_submit\_data**, which appears in bold.

The first section contains the XML input declaration of the variable SOAPTemplate, for a SOAP message:

```
#include "as_web.h"  
// SOAP message  
const char*      pSoapTemplate=  
    "<soap:Envelope xmlns:soap=\"http://schemas.xmlsoap.org/soap/envelope/\">"  
    "<soap:Body>"  
        "<SendMail xmlns=\"urn:EmailIPortTypeInft-IEmailService\"/>"  
    "</soap:Body>"  
</soap:Envelope>;
```

The following section represents the actions of the user:

```
Action1()
{
// get response body
    web_reg_save_param("ParamXml", "LB=", "RB=", "Search=body", LAST);
// fetch weather by HTTP GET
    web_submit_data("GetWeather", "Action=http://glkev.net.innerhost.com/glkev_ws/
        WeatherFetcher.asmx/GetWeather",
        "Method=GET",
        "EncType=",
        "RecContentType=text/xml",
        "Referer=http://glkev.net.innerhost.com
            /glkev_ws/WeatherFetcher.asmx?op=GetWeather",
        "Snapshot=t2.inf",
        "Mode=HTTP",
        ITEMDATA,
        "Name=zipCode", "Value=10010", ENDITEM,
        LAST);

// Get City value
    lr_xml_get_values("Xml={ParamXml}",
        "Query=City",
        "ValueParam=ParamCity",
        LAST
    );
    lr_output_message(lr_eval_string("***** City = {ParamCity} *****"));

// Get State value
    lr_xml_get_values("Xml={ParamXml}",
        "Query=State",
        "ValueParam=ParamState",
        LAST
    );
    lr_output_message(lr_eval_string("***** State ={ParamState}*****"));

// Get several values at once by using template
    lr_xml_get_values_ex("Xml={ParamXml}",
        "Template="
            "<Weather>

                "<Time>{ParamTime}</Time>"
                "<Temperature>{ParamTemp}</Temperature>"
                "<Humidity>{ParamHumid}</Humidity>"
                "<Conditions>{ParamCond}</Conditions>
            "</Weather>",
        LAST
    );
}
```

```

Lr_output_message(Lr_eval_string("***** Time = {ParamTime},
                                 Temperature = {ParamTemp}, "
                                 "Humidity = {ParamHumid},
                                 Conditions = {ParamCond} *****"));

// Generate readable forecast
Lr_save_string(Lr_eval_string("\r\n\r\n*** Weather Forecast for {ParamCity},
                               {ParamState} ***\r\n"
                               "\tTime: {ParamTime}\r\n"
                               "\tTemperature: {ParamTemp} deg. Fahrenheit\r\n"
                               "\tHumidity: {ParamHumid}\r\n"
                               "\t{ParamCond} conditions expected\r\n"
                               "\r\n"),
               "ParamForecast"
);

// Save soap template into parameter
Lr_save_string(pSoapTemplate, "ParamSoap");

// Insert request body into SOAP template
lr_xml_insert("Xml={ParamSoap}",
              "ResultParam=ParamRequest",
              "Query=Body/SendMail",
              "position=child",
              "XmlFragment="
                "<FromAddress>taurus@merc-int.com</FromAddress>"
                "<ToAddress>support@merc-int.com</ToAddress>"
                "<ASubject>Weather Forecast</ASubject>"
                "<MsgBody/>",
LAST
);
//
//<soap:Envelope xmlns:soap=\\"http://schemas.xmlsoap.org/soap/envelope/\\">
//  <soap:Body>
//    <SendMail xmlns=\"urn:EmailIPortTypeInft-IEmailService\"/>
//    <FromAddress>taurus@merc-int.com</FromAddress>
//    <ToAddress>support@merc-int.com</ToAddress>
//    <ASubject>Weather Forecast</ASubject>
//    <MsgBody/>
//  </SendMail>
//</soap:Body>
//</soap:Envelope>;
//
// Insert actual forecast text
lr_xml_set_values("Xml={ParamRequest}",
                  "ResultParam=ParamRequest",
                  "Query=Body/SendMail/MsgBody",
                  "ValueParam=ParamForecast",
LAST);

```

```
// Add header for SOAP
web_add_header("SOAPAction", "urn:EmailIPortTypeInft-IEmailService");
// Get response body
web_reg_save_param("ParamXml", "LB=", "RB=", "Search=body", LAST);
// Send forecast to recipient, using SOAP request
web_custom_request("web_custom_request",
    "URL=http://webservices.matlus.com/scripts/emailwebservice.dll/soap
     /IEmailservice",
    "Method=POST",
    "TargetFrame=",
    "Resource=0",
    "Referer=",
    "Body={ParamRequest}",
    LAST);
// Verify that mail was sent
lr_xml_find("Xml={ParamXml}",
            "Query=Body/SendMailResponse/return",
            "Value=0",
            LAST
        );
return 0;
}
```

## How to Use Result Parameters

Some of the **lr\_xml** functions return a result parameter, such as **ResultParam**. This parameter contains the resulting XML data after the function is executed. The result parameters will be available from the parameter list in the Select or Create Parameter dialog box.

For example, for **lr\_xml\_insert**, **ResultParam** contains the complete XML data resulting from the insertion of the new XML fragment


You can use the result parameters as input to other XML related functions such as Web Service calls. During replay, VuGen captures the value of the result parameter. In a later step, you can use that value as an input argument.

The functions that support result parameters are **lr\_xml\_insert**, **lr\_xml\_transform**, **lr\_xml\_replace**, **lr\_xml\_delete**, and **lr\_xml\_set\_values**.


The following functions save values to a parameter other than the **resultParam**: **lr\_xml\_get\_values** saves values to **ValueParam** and **lr\_xml\_extract** saves values to **XMLFragmentParam**. These values are also available for parameter substitution.

### Use the Result Parameter as Input

1. In the **Step Navigator**, double-click on an XML step to view its Properties.
2. In the Result XML Parameter box, specify a name for the **Result XML parameter** (or **ValueParam** and **XMLFragmentParam**).



3. Reference the parameter name as in input argument.



For more information, see ["New Web Service Call Dialog Box" on page 865](#).

## Troubleshooting and Limitations - Programming

### Framework 4.5 for .NET scripts

**Issue:** Running a .NET script recorded in VuGen, fails if you run it in Visual Studio—cannot find associated DLL.

**Steps to Resolve:** If the script was recorded with a .NET 4.5 AUT, rebuild the script with Framework version 4.5 in Visual Studio.

### Framework 4.5 and Visual Studio 2010

**Issue:** Compilation fails for all C++ projects on machines with Framework 4.5.

**Steps to Resolve:** Install Visual Studio 2010 SP1.

## Framework 3.5 for .NET scripts

**Issue:** .NET DLLs created in Visual Studio using Framework 3.5 may not run.

**Steps to Resolve:** Add the following to the **<app>.config file**: (if there is no such file, create one)

```
<configuration>
  <startup>
    <supportedRuntime version="v4.0" />
  </startup>
</configuration>
```

## Visual Studio Addin with C# user scripts

**Issue:** C# scripts in Visual Studio 2010, create .NET assemblies that need to be registered in the system before their run. Registration of the .NET assembly requires administrative permissions.

**Steps to Resolve:** There are 2 ways to register .NET assembly before run test:

1. Run Visual Studio "As Administrator" and provide administrative credentials when prompted. In Project Settings, ensure that the **Register for COM interop** option is set (**Project > Properties > Build > Register for COM interop**). Visual Studio will automatically register the test DLL as a .NET assembly every time it builds the project.
2. Run Visual Studio without administrative permissions, and manually register the test DLL after build. To do so, run Windows Console with administrative permissions and run the following command **%WINDIR%\Microsoft.NET\Framework\v4.0.30319\RegAsm.exe <TargetDLLwithPath> /codebase** (ignore the warning issued when you run this command.) For example, you might replace **<TargetDLLwithPath>** with "c:\users\qatest\documents\visual studio 2010\Projects\LoadRunnerUser1\LoadRunnerUser1\LoadRunnerUser1.dll". You do not need to register the DLL after every build. It is enough to register it once after making changes in the COM interfaces defined in the DLL.

For both options, make sure to keep UAC enabled. Otherwise, when you run Visual Studio or the Console "As Administrator", you will be not prompted for Administrative credentials and the applications will run with restricted user rights.

# Non-English Language Support

## Non-English Language Support - Overview

VuGen supports multilingual environments, allowing you to use languages other than English on native language machines when creating and running scripts.

When working with languages other than English, the primary issue is ensuring that VuGen recognizes the encoding of the text during record and replay. The encoding applies to all texts used by the script. This includes texts in HTTP headers and HTML pages for Web Vusers, data in parameter files, and others.

Windows 2000 and higher lets you save text files with a specific encoding directly from Notepad: ANSI, Unicode, Unicode big endian, or UTF-8.

By default, VuGen works with the local machine encoding (ANSI). Some servers working with foreign languages, require you to work with UTF-8 encoding. To work against this server, you must indicate in the Advanced recording options, that your script requires UTF-8 encoding.

## Page Request Header Language

Before running a Web script, you can set the page's request header to match your current language. In the Internet Protocol run-time settings, you set the language of the *Accept-Language* request header. This header provides the server with a list of all of the accepted languages.

To set this value, select **Replay > Run-Time Settings > Internet Protocol > Preferences > Advanced > Options > Accept-Language request header** and select the desired language.

For user interface details, see "["Internet Protocol > Preferences Node" on page 353](#)".

## How to Convert Encoding Format of a String

You can manually convert a string from one encoding to another (UTF-8, Unicode, or locale machine encoding) using the **lr\_convert\_string\_encoding** function with the following syntax:

```
lr_convert_string_encoding(char * sourceString, char * fromEncoding, char * toEncoding, char * paramName)
```

The function saves the result string (including its terminating NULL) in the third argument, *paramName*. It returns a 0 on success and -1 on failure.

The format for the **fromEncoding** and **toEncoding** arguments are:

LR_ENC_SYSTEM_LOCALE	NULL
LR_ENC_UTF8	"utf-8"
LR_ENC_UNICODE	"ucs-2"

In the following example, **lr\_convert\_string\_encoding** converts "Hello world" from the system locale to Unicode.

```
Action()
{
    int rc = 0;
    unsigned long converted_buffer_size_unicode = 0;
    char           *converted_buffer_unicode = NULL;
    rc = lr_convert_string_encoding("Hello world", NULL, LR_ENC_UNICODE, "string
InUnicode");
    if(rc < 0)
    {
        // error
    }
}
```

```
    }  
    return 0;  
}
```

In the replay log, the output window shows the following information:

Output:  
Starting action Action.  
Action.c(7): Notify: Saving Parameter "stringInUnicode = H\x00e\x001\x001\x000\x00 \x00w\x00o\x00r\x001\x00d\x00\"  
Ending action Action.

The result of the conversion is saved to the *paramName* argument.

## How to Convert Encoding Format of Parameter Files


The parameter file contains the data for parameters that were defined in the script. This file, stored in the script's folder, has a *\*.dat* extension. When running a script, Vusers use the data to execute actions with varying values.

By default, VuGen saves the parameter file with your machine's encoding. When working with languages other than English, however, in cases where the server expects to receive the string in UTF-8, you may need to convert the parameter file to UTF-8. You can do this directly from Notepad, provided that you are working with Windows 2000 or higher.

### Apply UTF-8 Encoding to a Parameter File

1. Select **Vuser > Parameter List** and view the parameter properties.
2. In the right pane, locate the parameter file in the **File path** box.
3. With the parameter table in view, click **Edit in Notepad**. Notepad opens with the parameter file in csv format.
4. In the **Save as type** box, select *All Files*.

In the **Encoding** box, select *UTF-8* type encoding.



5. Click **Save**. Notepad asks you to confirm the overwriting of the existing parameter file. Click **Yes**.

Vugen now recognizes the parameter file as UTF-8 text, although it still displays it in regular characters.

## How to Record Web Pages with Foreign Languages

When working with Web or other Internet protocols, you can indicate the encoding of the Web page text for recording. The recorded site's language must match the operating system language. You cannot mix encodings in a single recording—for example, UTF-8 together with ISO-8859-1 or shift\_jis.

This task describes how to record web pages with foreign languages using Vugen.

### Automatically Record Foreign Language Web Pages.

In order to be recognized as a non-English Web page, the page must indicate the charset in the HTTP header or in the HTML meta tag. Otherwise, Vugen will not detect the EUC-JP encoding and the Web site will not be recorded properly. To instruct Vugen to record non-English requests as **EUC-JP** or **UTF-8**, select **Record > Recording Options > HTTP Properties > Advanced > support charset** and select the appropriate option in the Recording Options dialog box, **HTTP Properties: Advanced** node. For user interface details, see "["HTTP > Advanced Node" on page 208](#)".

Note that by selecting the **EUC-JP** or **UTF-8** option in the Recording Options, you are forcing Vugen to record a Web page with the selected encoding, even when it uses different encoding. If,

for example, a non-EUC encoded Web page is recorded as EUC-JP, the script will not replay properly.

## Manually Record Foreign Language Web Pages

You can manually add full support for recording and replaying of HTML pages encoded in EUC-JP using the **web\_sjis\_to\_euc\_param** function. This also allows VuGen to display Japanese EUC-encoded characters correctly in Vuser scripts.

When you use **web\_sjis\_to\_euc\_param**, VuGen shows the value of the parameter in the Execution Log using EUC-JP encoding. For example, when you replay the **web\_find** function, VuGen displays the encoded values. These include string values that were converted into EUC by the **web\_sjis\_to\_euc\_param** function, or parameter substitution when enabled in the **Run-Time Setting > Log > Extended Log**.

# Foreign Languages - Troubleshooting and Limitations

This section describes troubleshooting and limitations when working with foreign languages.

## Script / Scenario Names

- When recording in COM, FTP, IMAP, SMTP, POP3, or REAL mode, the length of the script name is limited to 10 multi-byte characters (21 bytes).
- Script names and their paths must only contain English characters.
- The name and path of a scenario cannot contain multi-byte characters.
- When recording in COM, FTP, IMAP, SMTP, POP3, or REAL mode, the length of the script name is limited to 10 multi-byte characters (21 bytes).
- Script names and their paths must only contain English characters.
- Argument and parameter names should be in English.

## Browser Configuration

If, during recording, non-English characters in the script are displayed as escaped hexadecimal numbers (For example, the string " =;" becomes "%DC%26"), you can correct this by configuring your browser not to send URLs in UTF-8 encoding. In Internet Explorer, select **Tools > Internet Options** and click the **Advanced** tab. Clear the **Always Send URLs as a UTF-8** option in the Browsing section.

For more information about **web\_sjis\_to\_euc\_param**, see the LoadRunner Function Reference.

## Protocol Limitations

**SMTP:** If you work with the SMTP protocol through MS Outlook or Outlook Express, the Japanese text recorded in a Vuser script is not displayed correctly. However, the script records and replays correctly.

## Application Lifecycle Management Integration

To open a script saved in an Application Lifecycle Management project from VuGen, or a scenario saved in an ALM project from Controller, add a new Test Set named "Default" (in English) to the ALM project.

## ContentCheck in Multilingual Environments

- This version supports ContentCheck rules in French, German, Spanish, and Italian. The correct language file should be installed according to the system locale.
- The suitable language file can also be copied from the installation disk:  
..\\runner\\MSI\\setup\\international\\<lang>\\dat\\LrwiAed\\Installation.xml to the <LoadRunner>\\dat directory.

## Language Packs

- **Uninstalling LoadRunner:** LoadRunner fails to uninstall on a Chinese operating system if the LoadRunner installation path contains Chinese characters. **Workaround:** xxxx
- **Recording Functions:** LoadRunner cannot record a Vuser script for certain protocols if the LoadRunner installation is on a Chinese operating system, and the installation path contains Chinese characters. **Workaround:** xxxx
- LoadRunner User Interface Pack. While installing the Language Pack, a warning message may be displayed that the HP LoadRunner Launcher Process is in use.  
**Workaround:** Click **Continue** to resume the installation.
- The language pack of .NET Framework needs to be installed to show the localized strings.
- Tutorial scripts. After the Language Pack installation, all sessions and scripts in \\HP\\LoadRunner\\tutorial are still in English.
- LoadRunner User Interface Pack. If you are working with a LoadRunner User Interface Pack, it is recommended that you install it before running LoadRunner for the first time.
- Menus and toolbars. If you install a LoadRunner User Interface Pack after running LoadRunner for the first time, the menus and toolbars may not get translated.  
**Workaround:** Close LoadRunner and delete the following folder from the registry: HKEY\_CURRENT\_USER\\Software\\<Folder Name>, where <Folder Name> is the drive on which you installed LoadRunner.  
For example, if LoadRunner is installed on the C drive, the registry folder name would be: HKEY\_CURRENT\_USER\\Software\\C.Restart LoadRunner.
- Report Templates in Analysis. If you install a LoadRunner User Interface Pack after running LoadRunner for the first time, the Report Templates in Analysis (Reports > Report Templates) may not get translated.  
**Workaround:** Close LoadRunner and copy the files from: <LoadRunner User Interface Pack CD root>\\Reporting to folder <LoadRunner installation folder>\\bin\\dat\\Reporting. Restart LoadRunner.

## Non-Localized LoadRunner on Foreign Language Operating Systems

- **Language support.** LoadRunner only supports English and the native language of the machine's operating system. For example, if you are using Japanese Windows XP, you can work with LoadRunner in Japanese and in English.
- **Installation path.** The path in which installation files for LoadRunner are located, and the path in which LoadRunner is installed, can contain only English characters.
- **Diagnostics add-in.** To use the Diagnostics add-in with Controller on a computer with a non-English operating system the Diagnostics\_9.0\_8.0\_LR\_Addin\_QCCR1152206 hotfix should be installed. For further assistance, contact HP customer support.
- **.NET Framework 3.5 failure.** Installing LoadRunner on a localized machine may result in a failure in the .NET Framework 3.5 installation process, and you will be asked to terminate the installation. This happens because the .NET 3.5 Framework installation attempts to download the Framework Language Pack but fails.  
**Workaround:** Terminate the LoadRunner installation according to the Installation wizard's instructions and invoke the LoadRunner installation again.
- **Online Help.** The search functionality may not function as expected for strings that contain Chinese/Japanese characters (except Japanese full-width Katakana).  
**Workaround:** Add a half-width space after each character in the search string.
- **Online Help.** For optimum performance of the online Help, install the latest JRE.
- **Japanese characters in Web (HTTP/HTML) scripts.** If you set the advanced recording option to specify the encoding of an application, and the application uses different character encoding for different pages, then the recording log or script may display invalid Japanese characters. This does not cause any errors in the script replay.  
**Workaround:** Remove/add space(s) from/to the script so the comparison succeeds or specify regular expressions to avoid the issue.
- **Non-breaking spaces** in Web protocols for Far Eastern languages. A non-breaking space (&nbsp; ; &#160; ; &#xA0; ; '\xA0', etc.) cannot be represented in some Far Eastern locale character sets (in which it is considered a lead byte). Instead, non-breaking spaces are converted to regular spaces (' ', '\x20', etc.), both during script code generation and replay. This may cause replay problems, such as mismatches in length due to eliminating multiple regular spaces.  
**Workaround:** Remove/add space(s) from/to the script so the comparison succeeds or specify regular expressions to avoid the issue.
- **Standalone installations.** The installation interface of the VuGen and Analysis standalone are in English and not localized.
- **Flex AMF call properties.** Multibyte symbols in Flex AMF call properties will be corrupted in the script text view.
- **rdp\_type** The **rdp\_type** function does not support native language characters for both record and replay.
- **Transaction names:** Korean characters are not supported in transaction names.

- **Word Completion.** Word completion does not work when Windows is configured to use the Ctrl+Space combination. This is common when using a Chinese keyboard.  
**Workaround:** Select **Complete word** from the **Edit** menu. Advanced users can disable Ctrl+Space for Chinese keyboards, by setting the following registry keys:
  - [HKEY\_CURRENT\_USER\Control Panel\Input Method\Hot Keys\00000010]  
"Key Modifiers"=hex:00,c0,00,00  
"Target IME"=hex:00,00,00,00  
"Virtual Key"=hex:ff,00,00,00
  - [HKEY\_CURRENT\_USER\Control Panel\Input Method\Hot Keys\00000070]  
"Key Modifiers"=hex:00,c0,00,00  
"Target IME"=hex:00,00,00,00  
"Virtual Key"=hex:ff,00,00,00
- **ODBC and Oracle-2 Tier protocols.** When recording a script in VuGen using the ODBC or Oracle-2 Tier protocols, if you stop the recording while the AUT is still open, VuGen may crash.  
**Workaround:** Close LoadRunner and open the file <LoadRunner installation folder>\dat\protocols\options\script\general.opt in a text editor.  
Comment out the following line by adding a semicolon at the beginning of the line:  
Option=DumpProcesses so it looks like this: ;Option=DumpProcesses
- **PDF reports.** In Analysis, a PDF report may be generated with unreadable characters if it contains non-English characters.  
**Workaround:** Before you generate the PDF file, change the font in the Report Template that you are using.
  - a. Select **Reports > Report Templates**.
  - b. Select the template that you want to use.
  - c. In the Detailed Report section, select the Format tab.
  - d. For each UI element in the list, change the font to the desired font that supports the language in which the report is written.

## Additional Components

You can install additional components that provide advanced features for working with LoadRunner. You install these components from the following locations:

- The **Additional Components** folder inside the root folder of the LoadRunner installation DVD.
- **HP Software Support Online (Help > HP Software Support Site).** After logging in to the support site, search for "LR 12.00 Additional Components", and download the file that contains all the additional components. Unzip the file, and run the installation wizard for the additional component that you want to install.

The table below indicates which additional components are available, and where you should install each component:

Folder	Component	Description	Install on...
<b>Agent for Citrix Server</b>	Setup file	Installs the Citrix Agent which enhances VuGen's capabilities in identifying Citrix client objects during Citrix protocol record and replay. For installation instructions, see " <a href="#">Installing the Citrix Server Agent</a> " on page 1009.  The agent also enables you to use additional Citrix API functions. For details, see the <a href="#">LoadRunner Function Reference</a> .	Citrix Server
<b>Agent for Microsoft Terminal Server</b>	Setup file for MS Terminal Agent	Installs a utility that enhances the RDP protocol's recording mechanism in VuGen. For installation instructions, see " <a href="#">Installing the Microsoft Terminal Server Agent</a> " on page 1011.	RDP server
<b>Assembly Crawler for Analysis API</b>	Setup file for Assembly Crawler Console	Installs a command-line utility to build a .NET configuration file for a LoadRunner Analysis API application. For more information, open the <b>Analysis API Reference</b> from the <b>Start &gt; Documentation</b> menu (not available with VuGen Standalone).	LoadRunner Analysis machine
<b>HostID Generator</b>	Host ID Generator tool, licidgenerator.exe	Opens the Host ID Generator utility that displays the computer's Host ID. This is useful when requesting a license. For details, see " <a href="#">LoadRunner License Utility</a> " on page 1022.	LoadRunner Controller
<b>HP Performance Validation SDK</b>	Configuration Builder Setup file	Installs the <b>Configuration Builder</b> which allows you to create a custom protocol. For more information, after the installation, open the <b>Configuration Builder</b> from the LoadRunner group and access the <b>Help</b> menu.	VuGen machine
<b>IDE Add-Ins</b>	Add-in setup files for common versions of Visual Studio	Installs add-ins for Visual Studio enabling you to create Vuser scripts in your standard development environment using the LoadRunner API. This integration also allows you to run the test directly from Visual Studio, to test its functionality. For details, see " <a href="#">Creating Scripts in External IDEs</a> " on page 969.	Visual Studio machine with VuGen

Folder	Component	Description	Install on...
<b>IDE Add-Ins Dev</b>	Setup files for developer add-ins for Visual Studio 2010/ 2012 and Eclipse	Installs add-ins for Visual Studio or Eclipse, enabling you to create NUnit or JUnit tests in your standard development environment using the LoadRunner API. For details, see " <a href="#">Creating Scripts in External IDEs</a> " on page 969.	Visual Studio or Eclipse machine with VuGen
<b>LRTCPDump</b>	Command line executable for Windows and UNIX platforms	Creates a trace file containing logs of TCP traffic over the network. This can be used as an alternative to Wireshark.  For details, see " <a href="#">How to Create a Script by Analyzing Traffic</a> " on page 860.	Any machine with WinPcap (see below)
<b>mobile RemoteAgent</b>	Executable files for several platforms	Starts the Mongoose Web server to provide mobile functionality. For details, see " <a href="#">How to Record and Analyze a Script for Mobile Applications</a> " on page 707	Mobile AUT backend server
<b>SAP Tools</b>	Executable and help files for SapSpy and VerifyScripting	<ul style="list-style-type: none"> <li><b>SAPGUI Spy.</b> Examines the hierarchy of GUI Scripting objects, on open windows of <b>SAPGUI Client for Windows</b>.</li> <li><b>SAPGUI Verify Scripting.</b> Verifies that the SAPGUI Scripting API is enabled.</li> </ul> For details, see " <a href="#">How to Configure the SAP Environment</a> " on page 782.	VuGen machine with SAPGUI client
<b>Third Parties</b>	Source files	The folder contains the source code of some third party software components which are being used in LoadRunner. See the table below for information about some of these components.	
<b>Virtual Table Server</b>	Setup file	This installation runs the VTS setup through a wizard. For details, see " <a href="#">Installing VTS</a> " on page 1010.	Any machine

## Third Party Components

Folder	Component	Description	Install on...
<b>MQTester</b>	Zip file containing setup file for MQTester	Installs OpenText MQTester for HP LoadRunner. MQTester integrates with LoadRunner to provide the capability to load-test and stress-test WebSphere MQ-based systems.	LoadRunner or Load Generator machine
<b>WinPcap</b>	Setup file	Installs WinPcap, the Windows Packet Capture libraries, enabling you to capture network traffic into a file. This is useful for creating a Web Services or Mobile HTTP Vuser script from captured traffic. For details, see <a href="http://www.winpcap.org">http://www.winpcap.org</a> .  This is to be used in conjunction with the additional component, LRTCPDump.	Any machine

## Installing the Citrix Server Agent

The installation file for the Agent for Citrix Server is located on the LoadRunner installation DVD, in the **Additional Components\Agent for Citrix Server** folder.

**Note:** The agent should be installed on your Citrix server machine—not Load Generator machines.

If you are installing a newer version of an agent, make sure to first uninstall the previous version (see removal instructions below).

### To install the Agent for a Citrix Server:

1. If your server requires administrator permissions to install software, log in as an administrator to the server.
2. Locate the installation file, **Setup.exe**, on the product installation disk in the Additional Components\Agent for Citrix Server folder.
3. Follow the installation wizard to completion.

**Note:** After installation the agent is only active for LoadRunner invoked Citrix sessions—it is not active for users who start a Citrix session without LoadRunner.

To disable the agent, you must uninstall it.

### To uninstall the Agent for Citrix Server:

1. If your server requires administrator privileges to remove software, log in as an administrator to the server.
2. Open **Add/Remove Programs** in the server machine's Control Panel. Select **HP Software Agent for Citrix Server** and click **Change/Remove**.

## Installing VTS

Two versions of VTS are available: 32-bit and 64-bit. You can install 32-bit VTS on both 32-bit and 64-bit operating systems; 64-bit VTS can be installed only on 64-bit operating systems.

**Note:** Do not install 64-bit VTS and 32-bit VTS on the same machine.

To install VTS:

1. Run the appropriate VTS setup.exe file [**Win32** or **Win64**] that is located in the **Additional Components\Virtual Table Server** folder in the LoadRunner installation media. The VTS Setup Wizard opens, displaying the welcome page.
2. Follow the online instructions to complete the VTS installation.

**Note:** At the end of the installation process, a shortcut for VTS is created and added to your desktop. This shortcut gives you access to the VTS UI on the local machine. If you change the port that is used to access the VTS UI, you must manually update the **URL** property of the shortcut. For details on how to change the VTS UI access port, see **Configuring VTS** in the VTS online documentation.

If you are unable to access the VTS UI, make sure that the VTS Service service is started. To start the VTS Service service, go to Control Panel > Systems & Security > Administration Tools > Services. Right-click VTS Service and select Start.

If you are unable to access the VTS UI, make sure that the **VTS Service** service is started. To start the VTS Service service, go to **Control Panel > Systems & Security > Administration Tools > Services**. Right-click **VTS Service** and select **Start**.

### Configuring the VTS Administration Server

During the VTS installation process, you need to specify the port that is used to access the VTS server for administrative purposes.

#### To configure the VTS Administration server:

1. Begin the VTS installation process as described in "Installing Additional Components" on page 1. During the VTS installation process, the Configure VTS administration server screen appears.
2. In the **Admin UI server port** box, enter 4000.

3. Click **Next** to continue with the installation. The Configure VTS screen appears.
4. Specify where to save the VTS data file.
5. Make sure that the **Start Virtual Table Server Automatically** check box is selected.
6. Click **Next**, and then follow the wizard's instruction to complete the VTS installation procedure.

## Installing the Microsoft Terminal Server Agent

The installation file for the Agent for Microsoft Terminal Server is located on the product installation disk, under the Additional Components\Agent for Microsoft Terminal Server folder.

**Note:** The agent should be installed on your RDP server machine—not Load Generator machines.

If you are upgrading the agent, make sure to uninstall the previous version before installing the next one (see uninstallation instructions below).

### To install the Agent for Microsoft Terminal Server:

1. If your server requires administrator permissions to install software, log in as an administrator to the server.
2. Locate the installation file, **Setup.exe**, on the LoadRunner DVD in the **Additional Components\Agent for Microsoft Terminal Server** folder.
3. Follow the installation wizard to completion.

**Note:** To use the agent, you must set the recording options before recording a Vuser script. In the Start Recording dialog box, click **Options**. In the Advanced Code Generation node, check **Use RDP Agent**.

### To uninstall the Agent for Microsoft Terminal Server:

1. If your server requires administrator privileges to remove software, log in as an administrator to the server.
2. Open **Add/Remove Programs** in the server machine's Control Panel. Select **HP Software Agent for Microsoft Terminal Server** and click **Change/Remove**.

## Troubleshooting and Limitations - Additional Components

This sections contains troubleshooting and limitations for Additional Components.

### Secure Channels

- You cannot use the Host Security Manager utility to update security settings on Linux load generators that use rsh (remote shell) to connect to the Controller.
- You cannot use the Host Security Manager utility to change the security mode of the load generator located over a firewall from off to on.
- When the load generator is located over a firewall, if the load generator and Controller have different security modes, communication cannot be established.
- If the Controller machine is using secure channel communication, the MI Listener should not be installed on the same machine as the Controller.

# Controller

Welcome to the HP LoadRunner Controller User Guide. This guide presents an overview of the HP LoadRunner testing process, and describes how to create and run HP LoadRunner scenarios using HP LoadRunner Controller in a Windows environment.

HP LoadRunner is HP's tool for application performance testing. LoadRunner stresses your entire application to isolate and identify potential client, network, and server bottlenecks.

## Understanding LoadRunner LoadRunner Controller Overview

The Controller is LoadRunner's tool for creating and controlling LoadRunner *scenarios*. A scenario defines the events that occur during each testing session. It controls the number of users to emulate, the actions they perform, and the machines on which they run their emulations. You use scenarios to create load tests to check the reliability and strength of your servers. For details about load tests, see the ["Load Testing Overview" on page 1019](#).

The following are the primary items that you define in your scenario:

- **Scenario type.** A goal-oriented or manual scenario.
- **Tests.** The LoadRunner scripts or unit tests to run.
- **Machines.** The machines upon which to run the tests.
- **Vusers.** The number of virtual users (Vusers) to run on each machine.
- **Scheduling.** How to load the Vusers.
- **Monitors.** Which measurements to monitor during the test run.

When you open the Controller for the first time, it prompts you to select a type of scenario: goal-oriented or manual.

- **Goal-oriented** scenario. Define the goals you want your test to achieve and LoadRunner automatically builds a scenario for you based on these goals. For example you can define a goal for a specific number of Vusers to run simultaneously. Alternatively, you can define a goal to test your server performance such as Pages per Minute, Hits per Second, or Transactions per Second. For details, see ["Goals Types for Goal-Oriented Scenarios" on page 1041](#).
- **Manual** scenario. Add Vusers and select scripts/unit tests manually. You then distribute them on the available machines. For details, see ["Manual Scenarios" on page 1040](#).

## Scripts and Test Types


During a scenario run, the Controller runs Vuser scripts or system/unit tests. Vuser scripts are tests scripts created with the *LoadRunner Virtual User Generator*.

System/Unit tests refer to Selenium tests or *NUnit* and *JUnit* tests created in external development environments, such as Microsoft Visual Studio or Eclipse. You can work in your native application and prepare unit tests in binary form, such as .**dll** or .**jar** files, and then run them from the Controller.

**Note:** For more best practice information, see the LoadRunner Best Practices Forum.

LoadRunner add-ins allow you to integrate the LoadRunner API with MS Visual Studio or Eclipse, and run tests from your native environment. For details, see the section on Additional Components in the *LoadRunner Installation Guide*.

The Controller's opening dialog box prompts you to select the scripts and/or system/unit tests to include in the scenario. For details, see "["New Scenario Dialog Box" on page 1061](#)".



All of your selections, along with the test paths, are saved in a scenario file (.irs). You define all of the other aspects of your scenario in the Controller's **Design** tab. For details, see "["Design Tab" on page 1054](#)".


## Controller Workflow

The workflow below displays the key tasks for developing and running scenarios.



## Controller Technology

In the Controller, you define a number of Vusers (excluding GUI Vusers) to generate load on a server by submitting input directly to the server. Vusers do not operate client applications—they access the server using LoadRunner API functions. These API functions emulate the input from an actual application.



Because Vusers are not reliant on client software, you can use Vusers to test server performance even before the client software has been developed. Since Vusers do not have a user interface, the amount of system resources required is minimal. This allows you to run large numbers of Vusers on a single workstation.

The following example illustrates the use of Vusers in a scenario: Suppose that you have a Web-based database server that maintains your customer information. The information is accessed by numerous customer service personnel who are located throughout the country. The server receives the queries, processes the requests, and returns responses via the Web to field personnel.

You want to test the response times of the entire system when numerous service personnel simultaneously access the server. Using LoadRunner, you could create a scenario with several hundred Vusers, each one accessing the server database. The Vusers enable you to emulate and measure the performance of your database and Web servers under the load of many users.

To emulate the Vusers, you create a script to define their actions. A Vuser script includes functions that control the script execution and specify the input that the Vuser submits to the server. For more information, see "["Vuser Technology Overview" on page 64.](#)


For the database server example above, you could create a Vuser script that performs the following actions:

- Logs in to the Web application
- Connects to the database server
- Submits an SQL query

- Retrieves and processes the server response
- Disconnects from the server and the Web

## Controller Window

The Controller window enables you to design and run load test scenarios, monitor their metrics, and view Diagnostics for J2EE/.NET data.



<b>To access</b>	Choose one of the following: <ul style="list-style-type: none"><li>• <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Controller</b></li><li>• The Controller shortcut on the desktop</li></ul>
<b>Important information</b>	By default, upon opening the Controller, the New Scenario dialog box is displayed. To disable this option, clear the <b>Show at Startup</b> option. For details, see " <a href="#">"New Scenario Dialog Box" on page 1061</a> ".
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">"How to Design a Goal-Oriented Scenario" on page 1043</a></li><li>• <a href="#">"How to Design a Manual Scenario" on page 1045</a></li><li>• <a href="#">"How to Run a Scenario" on page 1191</a></li><li>• <a href="#">"How to Set Up a Monitoring Environment" on page 1259</a></li></ul>

User interface elements are described below:


UI Element	Description
	<b>New Scenario.</b> Opens New Scenario dialog box. For user interface details, see " <a href="#">"New Scenario Dialog Box" on page 1061</a> ".
	<b>Open Scenario.</b> Enables you to open an existing scenario.
	<b>Save Scenario.</b> Enables you to save the active scenario.
 (Goal-oriented scenario; Run view only)	<b>Edit scenario goal.</b> Opens the Edit Scenario Goal dialog box where you define goals for a goal-oriented scenario. For user interface details, see " <a href="#">"Edit Scenario Goal Dialog Box" on page 1056</a> ".
	<b>Load Generators.</b> Opens the Load Generators dialog box where you can add new load generators and view details about existing load generators. For user interface details, see " <a href="#">"Load Generators Dialog Box" on page 1101</a> ".
	<b>Show Network Virtualization Settings.</b> When Shunra Network Virtualization is installed on the machine, opens the " <a href="#">" Network Virtualization Settings Dialog Box" on page 1155</a> ".
 (Run view only)	<b>Initialize Vusers.</b> Initializes all Vusers (or those that are still in the <b>Down</b> state) in a selected Vuser group. The group's status changes from <b>Down</b> to <b>Pending</b> to <b>Initializing</b> to <b>Ready</b> . If the group fails to initialize, the status changes to <b>Error</b> . By initializing all of the Vusers in a group before running them, you can ensure that they all begin executing the scenario at the same time.
 (Run view only)	<p><b>Run Vusers Until Complete.</b> Runs all Vusers in a selected Vuser group until completion. If you run a Vuser group in the <b>Down</b> or <b>Error</b> state, LoadRunner initializes and then runs the group.</p> <p><b>Note:</b> You can instruct LoadRunner to randomly run only one Vuser in a Vuser group by right-clicking the group and selecting <b>Run one Vuser Until Complete</b>. A Vuser script log opens, displaying run-time information about the Vuser. For more information, see "<a href="#">"Vuser Script Log" on page 1216</a>".</p>
 (Run view only)	<b>Gradual Stop.</b> Gradually stops a Vuser group in the Run state if you selected the <b>Wait for the current iteration to end before exiting</b> or <b>Wait for the current action to end before exiting</b> options in the Run-Time Settings tab of the Options dialog box.
 (Run view only)	<b>Stop Vusers.</b> Immediately stops all Vusers in selected Vuser groups from executing their scripts.

 (Run view only)	<b>Analyze Results.</b> Opens diagnostics results.
	<b>Invoke VuGen.</b> Invokes HP Virtual User Generator.
	<b>Invoke Analysis.</b> Invokes HP LoadRunner Analysis.
<b>Design tab</b>	Enables you to design scenarios. For details, see " <a href="#">"Design Tab" on page 1054.</a>
<b>Diagnostics for J2EE/.NET tab</b>	Enables you to view J2EE/.NET diagnostics data collected from a scenario run. For details, see the section on Diagnostics.
<b>Run tab</b>	Enables you to run and monitor scenario runs. For details, see " <a href="#">"Run Tab" on page 1209.</a>
<b>&lt;Status bar&gt;</b>	Displays the following features of Controller (if enabled): <ul style="list-style-type: none"><li>• Application Lifecycle Management Connection</li><li>• IP Spoofing</li><li>• Auto Collate Results</li><li>• Auto Load Analysis</li></ul>

## HP LoadRunner Agents

To maximize your testing coverage, you distribute Vusers over several load generator machines. A load generator machine is a machine upon which the **Remote Agent Dispatcher (Process)** and a LoadRunner **Agent** are installed.

When you run the LoadRunner installation, you specify to install only these components. These components allow the Controller to communicate with the load generator machine.



- **Remote Agent Dispatcher.** The Remote Agent Dispatcher (Process) enables the Controller to start applications on the load generator.
- **Agent.** The LoadRunner Agent enables the Controller and the load generator to communicate with each other. When you run a scenario, the Controller instructs the Remote Agent Dispatcher (Process) to launch the LoadRunner agent. The agent receives instructions from the Controller to initialize, run, pause, and stop Vusers. At the same time, the agent also relays data on the status of the Vusers back to the Controller.

## Load Testing Overview

Modern system architectures are complex. While they provide an unprecedented degree of power and flexibility, these systems are difficult to test. Whereas single-user testing focuses primarily on functionality and the user interface of a system component, application testing focuses on performance and reliability of an entire system.

For example, a typical application testing scenario might depict 1000 users that log in simultaneously to a system on Monday morning. What is the response time of the system? Does the system crash? To be able to answer these questions and more, a complete application performance testing solution must do the following:

- Test a system that combines a variety of software applications and hardware platforms
- Determine the suitability of a server for any given application
- Test the server before the necessary client software has been developed
- Emulate an environment where multiple clients interact with a single server application
- Test an application under the load of tens, hundreds, or even thousands of potential users

The LoadRunner suite allows you to create load tests, which emulate the real life behavior of your application. For details, see "[The HP LoadRunner Solution](#)" on the next page.

## The HP LoadRunner Solution

Traditional or manual testing methods offer only a partial solution to load testing. For example, you can test an entire system manually by constructing an environment where many users work simultaneously on the system. Each user works at a single machine and submits input to the system. However, this manual testing method has the following drawbacks:

- It is expensive, requiring large amounts of both personnel and machinery.
- It is complicated, especially coordinating and synchronizing multiple testers.
- It involves a high degree of organization, especially to record and analyze results meaningfully.
- The repeatability of the manual tests is limited.

LoadRunner addresses the drawbacks of manual performance testing:

- LoadRunner reduces personnel requirements by replacing human users with virtual users or **Vusers**. These Vusers emulate the behavior of real users operating real applications.
- Because numerous Vusers can run on a single computer, LoadRunner reduces the amount of hardware required for testing.
- The HP LoadRunner Controller allows you to control all the Vusers from a single point of control.
- LoadRunner monitors the application performance online, enabling you to fine-tune your system during test execution.
- LoadRunner automatically records the performance of the application during a test. You can choose from a wide variety of graphs and reports to view the performance data.
- LoadRunner checks where performance delays occur: network or client delays, CPU performance, I/O delays, database locking, or other issues at the database server. LoadRunner monitors the network and server resources to help you improve performance.
- Because LoadRunner tests are fully automated, you can repeat them as often as you need.

## HP LoadRunner Terminology

- **Scenario.** A scenario is a sequence of events that emulate the hypothetical actions of real users on your application.
- **Vusers.** In the scenario, LoadRunner replaces real users with **virtual users** or **Vusers**. While a workstation accommodates only a single human user, many Vusers can run concurrently on a single workstation. In fact, a scenario can contain tens, hundreds, or even thousands of Vusers.
- **Vuser Scripts.** The actions that a Vuser performs during the scenario are described in a Vuser

script. When you run a scenario, each Vuser executes a **Vuser script**. The Vuser scripts include functions that measure and record the performance of your application's components.

- **Transactions.** To measure the performance of the server, you define **transactions**. A transaction represents an action or a set of actions that you are interested in measuring. You define transactions within your Vuser script by enclosing the appropriate sections of the script with **start** and **end** transaction statements. For example, you can define a transaction that measures the time it takes for the server to process a request to view the balance of an account and for the information to be displayed at the ATM.
- **Rendezvous points.** You insert **rendezvous points** into Vuser scripts to emulate heavy user load on the server. **Rendezvous points** instruct Vusers to wait during test execution for multiple Vusers to arrive at a certain point, so that they may simultaneously perform a task. For example, to emulate peak load on the bank server, you can insert a rendezvous point instructing 100 Vusers to deposit cash into their accounts at the same time.
- **Controller.** You use the HP LoadRunner Controller to manage and maintain your scenarios. Using the Controller, you control all the Vusers in a scenario from a single workstation.
- **Load Generator.** When you execute a scenario, the Controller distributes each Vuser in the scenario to a **load generator**. The load generator is the machine that executes the Vuser script, enabling the Vuser to emulate the actions of a human user.
- **Performance analysis.** Vuser scripts include functions that measure and record system performance during load-testing sessions. During a scenario run, you can monitor the network and server resources. Following a scenario run, you can view **performance analysis** data in reports and graphs.

## The HP LoadRunner Testing Process

The following section provides a general overview of the HP LoadRunner testing process.

### 1. Planning the Test

Successful load testing requires that you develop a thorough test plan. A clearly defined test plan will ensure that the LoadRunner scenarios that you develop will accomplish your load testing objectives. For more information, see "[Planning Load Test Scenarios](#)" on page 1030.

### 2. Creating the Vuser Scripts

Vusers emulate human users interacting with your Web-based application. A Vuser script contains the actions that each Vuser performs during scenario execution.

In each Vuser script, you determine the tasks that will be:

- Performed by each Vuser
- Performed simultaneously by multiple Vusers

- Measured as transactions

For more information on creating Vuser scripts, see "[Enhancing a Script for Load Testing - Overview](#)" on page 395.

### 3. Designing the Scenario

A scenario describes the events that occur during a testing session. A scenario includes a list of machines on which Vusers run, a list of scripts that the Vusers run, and a specified number of Vusers or Vuser groups that run during the scenario. When designing the scenario, you set the scenario configuration and scheduling which determines how all the load generators and Vusers behave while the scenario runs.

You design scenarios using the Controller. For information about LoadRunner scenarios, see "[Designing Scenarios](#)" on page 1040.

### 4. Running the Scenario

You emulate user load on the server by instructing multiple Vusers to perform tasks simultaneously. While the scenario runs, LoadRunner measures and records the transactions that you defined in each Vuser script. You can set the level of load by increasing and decreasing the number of Vusers that perform tasks at the same time and you can also monitor your system's performance online. For more information, see "[Running Scenarios](#)" on page 1190.

### 5. Monitoring the Scenario

You configure the LoadRunner monitoring components to identify bottlenecks on the system and determine which element is causing performance degradation, for example, file locking, resource contention, and network overload. Use LoadRunner in conjunction with the new network and machine monitoring tools to create load and measure performance at different points in the system. For more information on monitoring, see "[Working with LoadRunner Online Monitors](#)" on page 1258.

### 6. Analyzing Test Results

During scenario execution, LoadRunner records the performance of the application under different loads. You use LoadRunner's graphs and reports to analyze the application's performance. For more information about LoadRunner's reports and graphs, see "[Analysis](#)" on page 1350.

## License Utility

### ***LoadRunner License Utility***

To run Vusers from the LoadRunner Controller, you need the appropriate LoadRunner licenses. These licenses must be installed on the computer on which the LoadRunner Controller is installed. You use the LoadRunner License Utility to manage your LoadRunner licenses. The LoadRunner License Utility enables you to:

- View the details of licenses that are currently installed.
- Install additional licenses.

To access	Select <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; License &gt; LoadRunner License Utility</b> .
Important information	<p>Using the LoadRunner License Utility, you can install a new license by using either a license file or a license key.</p> <ul style="list-style-type: none"><li>• <b>License file.</b> When you purchase a new license, HP may send you an email with an attached license file. The license file contains the license keys for one or more licenses. When you use the license file to install the new licenses, the LoadRunner License Utility reads the license file and extracts all the license keys that are included in the license file. You can then select which of the available licenses to install. You may choose to use a license file to install LoadRunner licenses because the license file enables you to install multiple licenses simultaneously.</li><li>• <b>License key.</b> Unlike a license file, a license key enables you to install just a single license at a time. You may receive the license key directly from HP, or the license key may be included in a license file that you receive from HP.</li></ul>
Relevant tasks	<a href="#">"How to Install a New License" on page 1029</a>
See also	<a href="#">"Additional Information About VUD Licenses" on page 1029</a>

The table below describes the LoadRunner License Utility UI elements:

UI Element	Description
Host ID	Identifies the computer on which the Controller is installed. You may need to provide the Host ID when purchasing new LoadRunner licenses. To obtain new LoadRunner licenses, click the <b>Contact HP to purchase a new license</b> link at the bottom of the LoadRunner License Utility.
License Summary	Displays a list of the LoadRunner licenses that are installed on the Controller computer. Click on any license in the table to display additional details about the license. The <b>Vuser protocols included in the selected license</b> box displays a list of the Vuser protocols that are included in the selected license.

UI Element	Description
Status	<p>Indicates the status of the license.</p> <ul style="list-style-type: none"><li>• <b>Valid</b>  . Indicates that the license is current and functional.</li><li>• <b>Invalid</b>  . Indicates that the license is no longer valid.<ul style="list-style-type: none"><li>▪ A time-limited license becomes invalid after its expiration date passes.</li><li>▪ A <b>Time limited</b>, <b>Permanent</b>, or <b>VUD</b> license is installed for the same Vuser bundle.</li><li>▪ A <b>VUD</b> license becomes invalid when the remaining capacity is zero.</li></ul></li></ul> <p>By default, the License Summary table does not show invalid licenses. Select the <b>Show invalid licenses</b> check box to show invalid licenses.</p> <div data-bbox="567 846 1367 994" style="background-color: #f0f0f0; padding: 10px;"><p>Note that a license may become temporarily invalid if the LoadRunner License Utility detects that the system clock has been tampered with. To restore the affected licenses, reset the system clock to the current date and time.</p></div> <ul style="list-style-type: none"><li>• <b>To be Expired</b>  . Indicates that the license will expire within 30 days.</li></ul>
Locked	<p><b>Locked.</b> Indicates that the license can be installed only on the computer on which it is currently installed – not on any other computer.</p> <p><b>Unlocked.</b> Indicates that the license can be installed on any computer.</p>

UI Element	Description
License Bundle	<p>Indicates the name of the Vuser protocol bundle to which the license applies. The license enables the Controller to run Vusers of any protocol that is included in the protocol bundle. To display a list of the Vuser protocols that are included in a bundle, click the license in the License Summary table. A list of the associated Vuser protocols is displayed at the bottom of the LoadRunner License Utility.</p> <p>In addition to any other bundle you may purchase, LoadRunner is delivered with the <b>Community Bundle</b> which includes:</p> <ul style="list-style-type: none"> <li>• A permanent license with 50 Vusers.</li> <li>• Access to all the protocols with the exception of GUI (UFT), COM/DCOM and all the protocols in the template bundle.</li> </ul> <div data-bbox="551 804 1367 1026" style="background-color: #f0f0f0; padding: 10px;"> <p>Note that a <b>Partner License</b> icon  that appears to the left of a license bundle indicates that the license is for a LoadRunner partner, and not for standard LoadRunner Vuser protocols. Partner licenses enable third-party applications to be controller by the LoadRunner Controller. Partner licenses operate the same as standard LoadRunner licenses.</p> </div>
Type	<p>Indicates the type of license:</p> <ul style="list-style-type: none"> <li>• <b>Time limited</b> licenses are valid for a limited period only. <b>Time limited</b> licenses are typically issued for 60 or 365 days.</li> <li>• <b>Permanent</b> licenses do not expire - there is no time limit to the validity of these licenses.</li> <li>• <b>VUD</b> licenses are issued with a limited capacity. The capacity is defined by the measurement <i>Vuser-days</i> or <i>VUDs</i>. For example, the capacity of a VUD license may be 1000 VUDs. Each day that the Controller is used to run Vusers, the maximum number of Vusers that ran simultaneously on that day is deducted from the remaining license capacity. If a maximum of 200 Vusers ran on day 1, then 800 VUDs will remain in the license.</li> </ul> <div data-bbox="584 1607 1367 1702" style="background-color: #f0f0f0; padding: 10px;"> <p>Note that a VUD license may have an expiration date and therefore be time-limited.</p> </div> <p>For more information, see "<a href="#">Additional Information About VUD Licenses</a>" on page 1029.</p>
Expiration Date	Indicates the date and time when <b>Time limited</b> , <b>Instant on</b> , <b>VUD</b> , and <b>Evaluation</b> licenses expire.

UI Element	Description
Capacity	<ul style="list-style-type: none"> <li>For <b>Evaluation</b>, <b>Time Limited</b>, and <b>Permanent</b> licenses, <b>Capacity</b> indicates the maximum number of Vusers [of the type specified by the license bundle] that can be run simultaneously from the LoadRunner Controller.</li> <li>For VUD licenses, <b>Capacity</b> indicates the number of VUDs that remain in the license.</li> </ul>
Show invalid licenses	Select this check box to show invalid licenses in the list of LoadRunner licenses that are installed.
Vuser protocols included in the selected license	Displays the Vuser protocols that are included in the selected license.
Install New Licenses	Opens the New License dialog box which enables you to install new LoadRunner licenses. For details, see " <a href="#">How to Install a New License</a> " on page 1029.

## LoadRunner License Utility - New License

The LoadRunner License Utility - New License dialog box enables you to install a new license by using either a license file or a license key.

- License file.** When you purchase a new license, HP may send you an email with an attached license file. The license file contains the license keys for one or more licenses. When you use the license file to install the new licenses, the LoadRunner License Utility reads the license file and extracts all the license keys that are included in the license file. You can then select which of the available licenses to install. You may choose to use a license file to install LoadRunner licenses because the license file enables you to install multiple licenses simultaneously.
- License key.** Unlike a license file, a license key enables you to install just a single license at a time. You may receive the license key directly from HP, or the license key may be included in a license file that you receive from HP.

To access	Select <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; License &gt; LoadRunner License Utility</b> , and then click <b>Install New Licenses</b> .
Important information	Before you install a new LoadRunner license, ensure that you have the required license file or license key.
Relevant tasks	<a href="#">"How to Install a New License" on page 1029</a>
See also	<a href="#">"Additional Information About VUD Licenses" on page 1029</a>

The table below describes the LoadRunner License Utility - New License dialog box UI elements:

UI Element	Description
Install licenses using a license file	Select this option if you want to use a license file to install the new licenses.
License File	Click <b>Browse</b> and then select the license file that was sent to you by HP.
View License File Content	Displays the content of the license file in the table below.
Select the licenses to install	Select the check boxes for the licenses to install.
Install	Indicates the name of the Vuser protocol bundle to which the license applies. The license enables the Controller to run Vusers of any protocol that is included in the protocol bundle.
License Bundle	Indicates the name of the Vuser protocol bundle to which the license applies. The license enables the Controller to run Vusers of any protocol that is included in the protocol bundle.  In addition to any other bundle you may purchase, LoadRunner is delivered with the <b>Community Bundle</b> which includes: <ul style="list-style-type: none"><li>• A permanent license with 50 Vusers.</li><li>• Access to all the protocols with the exception of GUI (UFT), COM/DCOM and all the protocols in the template bundle.</li></ul>

UI Element	Description
Type	<p>Indicates the type of license:</p> <ul style="list-style-type: none"> <li>• <b>Evaluation</b> licenses are supplied to enable potential customers to evaluate LoadRunner functionality.</li> <li>• <b>Time limited</b> licenses are valid for a limited period only. <b>Time limited</b> licenses are typically issued for 60 or 365 days.</li> <li>• <b>Permanent</b> licenses do not expire - there is no time limit to the validity of these licenses.</li> <li>• <b>VUD</b> licenses are issued with a limited capacity. The capacity is defined by the measurement <i>Vuser-days</i> or <i>VUDs</i>. For example, the capacity of a VUD license may be 1000 VUDs. Each day that the Controller is used to run Vusers, the maximum number of Vusers that ran simultaneously on that day is deducted from the remaining license capacity. For example, if a maximum of 200 Vusers ran on day 1, then 800 VUDs will remain in the license. For the calculation of used VUDs, you can specify at what time each new day begins. To change the time at which a new day begins, click the <b>VUDs will begin at</b> link at the bottom of the LoadRunner License Utility.</li> </ul> <div data-bbox="567 1036 1356 1115" style="background-color: #f0f0f0; padding: 10px;"> <p>Note that a VUD license may have an expiration date and therefore be time-limited.</p> </div> <p>For more information, see "<a href="#">Additional Information About VUD Licenses</a>" <a href="#">on the next page</a>.</p>
Expiration Date	Indicates the date and time when <b>Time limited</b> , <b>VUD</b> , and <b>Evaluation</b> licenses expire.
Capacity	<ul style="list-style-type: none"> <li>• For <b>Evaluation</b>, <b>Time Limited</b>, and <b>Permanent</b> licenses, <b>Capacity</b> indicates the maximum number of Vusers [of the type specified by the license bundle] that can be run simultaneously from the LoadRunner Controller.</li> <li>• For VUD licenses, <b>Capacity</b> indicates the number of VUDs that remain in the license.</li> </ul>
Install a license using a license key	Select this option if you want to use a license key to install the new license, and then enter the license key that was sent to you by HP.
Install	Installs the licenses contained in the license file or license key.
Close	Closes the LoadRunner License Utility - New License dialog box.

## How to Install a New License

For information about LoadRunner licenses, see "[LoadRunner License Utility](#)" on page 1022.

To install a new LoadRunner license:

1. Select **Start > All Programs > HP Software > HP LoadRunner > License > LoadRunner License Utility**.
2. In the LoadRunner License Utility, click **Install New Licenses**. The LoadRunner License Utility - New License dialog box opens.

### To install using a license file

- a. Click the **Browse** button to the right of **License File**, and locate the license file that was sent to you by HP.
- b. Click **View License File Content** to display details of the licenses that are included in the license file.
- c. In the list of licenses included in the license file, select the licenses to install.

### To install using a license key

- a. Click **Install a license using a license key**.
- b. Enter the license key that you received from HP.
3. Click **Install**. The selected licenses are installed.
4. Click **Close**. In the License Summary table, make sure that the new licenses appear in the list of installed licenses.

## Additional Information About VUD Licenses

To run Vusers from the LoadRunner Controller, you need the appropriate LoadRunner licenses. There are various types of LoadRunner licenses. **VUD** licenses are issued with a limited capacity. The capacity is defined by the measurement *Vuser-days* or *VUDs*. For details on how to install VUD licenses, see "[LoadRunner License Utility](#)" on page 1022.

### Additional information about VUD licenses:

- For the calculation of VUDs consumed in a VUD license, you can specify at what time each new day begins. LoadRunner determines the maximum number of Vusers that ran during the 24 hour period after the start time. To change the time at which a new day begins, click the **VUDs will start at time** link at the bottom of the LoadRunner License Utility.
- If you have both a regular license [Instant On, Evaluation, Time limited, or Permanent] and a VUD license for a particular Vuser protocol, LoadRunner will always use the regular license

before deducting from the VUD license. Thus, if 500 Vusers were run on a particular day, and there is a regular license for 400 Vusers, then 100 VUDs will be deducted from the VUD license.

- A Vuser is included in the VUD count as soon as the Vuser reaches the Initialization status in a scenario.
- Consumed VUDs are deducted from the available VUD capacity at the start of the following day.
- If a scenario runs for more than one day, the maximum VUD usage is calculated and deducted based on the day that the scenario run started.
- A multi-protocol Vuser will run only if licenses are available for all protocols in the Vuser script. Therefore, if a Vuser script includes protocols from two different protocol bundles, you will need licenses for both bundles to run the Vuser script.
- A VUD license may have an expiration date and therefore be time-limited.

## Designing Load Test Scenarios

### Planning Load Test Scenarios

#### ***Load Test Planning Overview***

As in any type of system testing, a well-defined test plan is the first essential step to successful testing. Planning your load testing helps you to:

- Build test scenarios that accurately emulate your working environment.

Load testing means testing your application under typical working conditions, and checking for system performance, reliability, capacity, and so forth.

Before running your load test, it is important to:

- Understand which resources are required for testing.

Application testing requires hardware, software, and human resources. Before you begin testing, you should know which resources are available and decide how to use them effectively.

- Define success criteria in measurable terms.

Focused testing goals and test criteria ensure successful testing. For example, it is not enough to define vague objectives like "Check server response time under heavy load." A more focused success criterion would be "Check that 50 customers can check their account balance simultaneously, and that the server response time will not exceed one minute."

## Load Testing Objectives


Your test plan should be based on a clearly defined testing objective.

The following table presents common application testing objectives that LoadRunner helps you test. Each objective is described in detail after the table.

Objective	Answers the Question
Measuring end-user response time	How long does it take to complete a business process?
Defining optimal hardware configuration	Which hardware configuration provides the best performance?
Checking reliability	How hard or long can the system work without errors or failures?
Checking hardware or software upgrades	How does the upgrade affect performance or reliability?
Evaluating new products	Which server hardware or software should you choose?
Measuring system capacity	How much load can the system handle without significant performance degradation?
Identifying bottlenecks	Which element is slowing down response time?

### Measuring End-User Response Time

Check how long it takes for the user to perform a business process and receive a response from the server. For example, suppose that you want to verify that while your system operates under normal load conditions, the end users receive responses to all requests within 20 seconds. The following graph presents a sample load vs. response time measurement for a banking application:



### Defining Optimal Hardware Configuration

Check how various system configurations (memory, CPU speed, cache, adaptors, modems) affect performance. Once you understand the system architecture and have tested the application response time, you can measure the application response for different system configurations to determine which settings provide the desired performance levels.

For example, you could set up three different server configurations and run the same tests on each configuration to measure performance variations.

## Checking Reliability

Determine the level of system stability under heavy or continuous work loads. You can use LoadRunner to create stress on the system: force the system to handle extended activity in a compressed time period to simulate the kind of activity a system would normally experience over a period of weeks or months.

## Checking Hardware or Software Upgrades


Perform regression testing to compare a new release of hardware or software to an older release. You can check how an upgrade affects response time (benchmark) and reliability. Application regression testing does not check new features of an upgrade; rather it checks that the new release is as efficient and reliable as the older release.

### Evaluating New Products

You can run tests to evaluate individual products and subsystems during the planning and design stage of a product's life cycle. For example, you can choose the hardware for the server machine or the database package based on evaluation tests.


## Identifying Bottlenecks

You configure the LoadRunner monitoring components to identify bottlenecks on the system and determine which element is causing performance degradation, for example, file locking, resource contention, and network overload. Use LoadRunner in conjunction with the new network and machine monitoring tools to create load and measure performance at different points in the system. For more information on monitoring, see "[Monitoring Process Overview](#)" on page 1258.



## Measuring System Capacity

Measure system capacity, and determine how much excess capacity the system can handle without performance degradation. To check capacity, you can compare performance versus load on the existing system, and determine where significant response-time degradation begins to occur. This is often called the "knee" of the response time curve.



Once you determine the current capacity, you can decide if resources need to be increased to support additional users.

## How to Plan a Load Test

This task describes how to plan a load test.

### 1. Analyze the application

You should become thoroughly familiar with the hardware and software components, the system configuration, and the typical usage model. This analysis ensures that the testing environment you create using LoadRunner will reflect the environment and configuration of the application under test. For task details, see "[How to Analyze the Application](#)" below.

### 2. Define the load testing objectives

Before you begin testing, you should define exactly what you want to accomplish. For task details, see "[How to Define the Load Test Objectives](#)" on page 1036.

### 3. Plan LoadRunner implementation

Decide how to use LoadRunner to achieve your testing goals. For task details, see "[How to Plan the LoadRunner Implementation](#)" on page 1037.

## How to Analyze the Application


This task describes how to analyze the application under test as part of the load test planning process. Each step in this task contains example information relating to an online banking system.

## 1. Identify system components

Draw a schematic diagram to illustrate the structure of the application. If possible, extract a schematic diagram from existing documentation. If the application under test is part of a larger network system, you should identify the component of the system to be tested. Make sure the diagram includes all system components, such as client machines, network, middleware, and servers.

### Example

The following diagram illustrates an online banking system that is accessed by many Web users. The Web users each connect to the same database to transfer funds and check balances. The customers connect to the database server through the Web, using multiple browsers.



## 2. Describe the system configuration

Enhance the schematic diagram with more details. Describe each system component's configuration. You should be able to answer the following questions:

- How many users are anticipated to connect to the system?
- What is the application client's machine configuration (hardware, memory, operating system, software, development tool, and so forth)?
- What types of database and Web servers are used (hardware, database type, operating system, file server, and so forth)?
- How does the server communicate with the application client?
- What is the middleware configuration and application server between the front-end client and back-end server?

- What other network components may affect response time (modems and so forth)?
- What is the throughput of the communications devices? How many concurrent users can each device handle?

#### Example

The schematic diagram of the online banking system specified that there are multiple application clients accessing the system.

#### Front-End Client Configuration

Anticipated number of application clients	50 concurrent application clients
Hardware / Memory	Dual 2.27 GHz Intel Xeon
Operating system & version	Windows NT 6.1
Client browser	Internet Explorer 9

### 3. Analyze the usage mode

Define how the system is typically used, and decide which functions are important to test. Consider who uses the system, the number of each type of user, and each user's common tasks. In addition, consider any background load that might affect the system response time.

#### Example

Suppose 200 employees log on to the accounting system every morning, and the same office network has a constant background load of 50 users performing various word processing and printing tasks. You could create a LoadRunner scenario with 200 virtual users signing in to the accounting database, and check the server response time.

To check how background load affects the response time, you could run your scenario on a network where you also simulate the load of employees performing word processing and printing activities.

### 4. Examine task distribution

In addition to defining the common user tasks, examine the distribution of these tasks.

#### Example

Suppose the bank uses a central database to serve clients across many states and time zones. The 250 application clients are located in two different time zones, all connecting to the same Web server. There are 150 in Chicago and 100 in Detroit. Each begins their business day at 9:00 AM, but since they are in different time zones, there should never be

more than 150 users signing in at any given time. You can analyze task distribution to determine when there is peak database activity, and which activities typically occur during **peak load** time.

## How to Define the Load Test Objectives

This task describes how to define the load test objectives as part of the load test planning process.

### 1. Decide on general objectives

For a list of suggested testing objectives, see "[Load Testing Objectives](#)" on page 1031.

### 2. State the objectives in measurable terms

Once you decide on your general load testing objectives, you should identify more focused goals by stating your objectives in measurable terms. To provide a baseline for evaluation, determine exactly what constitutes acceptable and unacceptable test results.

#### Example

**General Objective.** Product Evaluation: choose hardware for the Web server.

**Focused Objective.** Product Evaluation: run the same group of 300 virtual users on two different servers, HP and NEC. When all 300 users simultaneously browse the pages of your Web application, determine which hardware gives a better response time.

### 3. Decide when to test

Load testing is necessary throughout the product life cycle. The following table illustrates what types of tests are relevant for each phase of the product life cycle:

Planning and Design	Development	Deployment	Production	Evolution
Evaluate new products	Measure response time	Check reliability	Measure response time	Check HW or SW upgrades
Measure response time	Check optimal hardware configuration	Measure response time	Identify bottlenecks	Measure system capacity
	Check HW or SW upgrades	Measure system capacity		
	Check reliability			

## ***How to Plan the LoadRunner Implementation***


This task describes how to plan the LoadRunner implementation as part of the load test planning process.

## **1. Define the scope of performance measurements**


You can use LoadRunner to measure **response time** at different points in the application. Determine where to run the Vusers and which Vusers to run according to the test objectives:

- **Measuring end-to-end response time.** You can measure the response time that a typical user experiences by running a GUI Vuser at the front end. GUI Vusers emulate real users by submitting input to and receiving output from the client application.

You can run GUI Vusers at the front end to measure the response time across the entire network, including a terminal emulator or GUI front end, network, and server.




- **Measuring network and server response times.** You can measure network and server response time, excluding response time of the GUI front end, by running Vusers (not GUI) on the client machine. Vusers emulate client calls to the server without the user interface. When you run many Vusers from the client machine, you can measure how the load affects network and server response time.




- **Measuring GUI response time.** You can determine how the client application interface affects response time by subtracting the previous two measurements:


GUI response time = end-to-end - network and server



- **Measuring server response time.** You can measure the time it takes for the server to respond to a request without going across the network. When you run Vusers on a machine directly connected to the server, you can measure server performance.



- **Measuring middleware-to-server response time.** You can measure response time from the server to middleware if you have access to the middleware and its API. You can create Vusers with the middleware API and measure the middleware-server performance.



## 2. Define Vuser activities

Create Vuser scripts based on your analysis of Vuser types, their typical tasks, and your test objectives. Since Vusers emulate the actions of a typical end-user, the Vuser scripts should include the typical end-user tasks. For example, to emulate an online banking client, you should create a Vuser script that performs typical banking tasks. You would browse the pages that you normally visit to transfer funds or check balances.

You decide which tasks to measure based on your test objectives and define **transactions** for these tasks. Transactions measure the time that it takes for the server to respond to tasks submitted by Vusers (end-to-end time). For example, to check the response time of a bank Web server supplying an account balance, define a transaction for this task in the Vuser script.

In addition, you can emulate peak activity by using **rendezvous points** in your script. Rendezvous points instruct multiple Vusers to perform tasks at exactly the same time. For example, you can define a rendezvous to emulate 70 users simultaneously updating account information.

### 3. Select Vusers

Before you decide on the hardware configuration to use for testing, determine the number and type of Vusers required. To decide how many Vusers and which types to run, look at the typical usage model, combined with the testing objectives. Some general guidelines are:

- Use one or a few GUI users to emulate each type of typical user connection.
- Run multiple Vusers to generate the rest of the load for each user type.

For example, suppose that you have five kinds of users, each performing a different business process:

Usage Model	GUI	Other
100 customer service users in New York (LAN connection)	2	98
30 customers in Europe (dial-in ISDN connection)	2	28
5 background batch processes	—	5
150 customers (terminal connection)	—	—
6 managers	2	4

### 4. Choose testing hardware/software

The hardware and software should be powerful and fast enough to emulate the required number of virtual users. Refer to the *HP LoadRunner Installation Guide* for specific hardware requirements.

To decide on the number of machines and correct configuration, consider the following:

- It is advisable to run HP LoadRunner Controller on a separate machine.
- Each GUI Vuser requires a separate Windows-based machine; several GUI Vusers can run on a single Linux machine.
- Configuration of the test machine for GUI Vusers should be as similar as possible to the actual user's machine.

**Note:** The results file requires a few MB of disk space for a long scenario run with many transactions. The load generators also require a few MB of disk space for temporary files if there is no NFS. For more information about run-time file storage, see "[Run-Time File Storage Locations](#)" on page 1170.

## Designing Scenarios

### Manual Scenarios

You build a manual scenario by selecting scripts to run, assigning load generators on which to run the scripts, and distributing Vusers to run among the scripts.

You can design a manual scenario in one of the following modes:

- **Vuser group mode.** In this mode, each script you select for the scenario is assigned to a Vuser group. You assign a number of Vusers to each Vuser group that you create. You can instruct all Vusers in a group to run the same script on the same load generator, or you can assign different scripts and load generators to the various Vusers in a group.
- **Percentage mode.** In this mode, you define a total number of Vusers to be used in the scenario, and assign load generators and a percentage of the total number of Vusers to each script.

After you define which Vuser groups/scripts to run in the scenario, you select or build a **schedule** by which to run the scenario. For more information, see "[Scheduling Manual Scenarios](#)" on page 1116.

You can also create **Service Level Agreements (SLAs)** which are specific goals that you define for your load test scenario. When you run the scenario, LoadRunner gathers and stores performance-related data. When you analyze the run, Analysis compares this data against the SLAs and determines SLA statuses for the defined measurements. For more information, see "[Service Level Agreements](#)" on page 1129.

### Changing Scenario Modes

You can convert a scenario from the Vuser group mode to the percentage mode and vice versa.

The following table describes what happens to the scenario when converting from the one mode to the other:

<b>Vuser group mode to percentage mode</b>	<ul style="list-style-type: none"><li>If a Vuser group contains multiple scripts, in percentage mode the scripts are listed one by one in the Scenario Scripts pane.</li><li>In the percentage mode, all load generators are assigned to all Vuser scripts by default. If multiple load generators are assigned to a Vuser group, the Vusers assigned to the scripts in the percentage mode are distributed evenly among the load generators originally assigned to the group.</li></ul> <p>If you defined group schedules for the Vuser groups, these settings will be lost. All profiles will contain schedule <b>by scenario</b> settings only. For details about scheduling scenarios, see "<a href="#">Scheduling Manual Scenarios</a>" on page 1116.</p>
<b>Percentage mode to Vuser group mode</b>	<ul style="list-style-type: none"><li>Each script is converted to a Vuser group.</li><li>If you defined multiple load generators for a Vuser script, the Vuser group that is created when converting the scenario will also contain multiple load generators.</li><li>If a schedule is defined for the scenario, all the schedule settings remain unchanged.</li></ul>

**Note:** You can convert from one scenario mode to another at any time. For details, see "[How to Change the Scenario Mode \(Manual Scenario\)](#)" on page 1047.

## Goals Types for Goal-Oriented Scenarios

In a goal-oriented scenario, you define the goals you want your test to achieve and LoadRunner automatically builds a scenario for you based on these goals.

You can define the following types of goals for a goal-oriented scenario:

- Virtual Users**

This goal tests if your application can run a specified number of Vusers simultaneously. Running this type of goal-oriented scenario is similar to running a manual scenario.

- Pages per Minute/Hits per Second/Transactions per Second**

These goals test the strength of your server. For each of these goal types, you specify a minimum-maximum range of Vusers for the scenario to run, and in the case of the Transactions per Second goal type, you also specify a transaction name.

**Note:**

- Pages per Minute** and **Hits per Second** goals are for Web Vusers only.
- Hits per second relates to HTTP requests per second.

When you define one of these goal type, the Controller divides the target defined by the minimum number of Vusers specified, and determines the target number of hits/transactions per second or pages per minute that each Vuser should reach.

The Controller then begins loading the Vusers according to the load behavior settings you defined, as follows:

- If you selected to run the Vusers automatically, LoadRunner loads 50 Vusers in the first batch. If the maximum number of Vusers defined is less than 50, LoadRunner loads all of the Vusers simultaneously.
- If you chose to reach your target after a certain period of the scenario elapses, LoadRunner attempts to reach the defined target within this period of time. It determines the size of the first batch of Vusers based on the time limit you defined and the calculated target number of hits, transactions, or pages per Vuser.
- If you chose to reach your target by gradation (x number of pages/hits every x amount of time), LoadRunner calculates the target number of hits or pages per Vuser and determines the size of the first batch of Vusers accordingly. (Not relevant for the Transactions per Second goal type).

After running each batch of Vusers, LoadRunner evaluates whether the target for the batch was achieved. If the batch target was not reached, LoadRunner recalculates the target number of hits, transactions, or pages per Vuser, and readjusts the number of Vusers for the next batch to be able to achieve the defined goal. By default, a new batch of Vusers is released every two minutes.

If the goal has not been reached after the Controller has launched the maximum number of Vusers, LoadRunner attempts to reach the defined target once more by recalculating the target number of hits, transactions, or pages per Vuser, and running the maximum number of Vusers simultaneously.

A Pages per Minute or Hits/Transactions per Second goal-oriented scenario is assigned a **Failed** status if:

- The Controller has twice attempted to reach the goal using the maximum number of Vusers specified, and the goal could not be reached.
- No pages per minute or hits/transactions per second were registered after the first batch of Vusers was run.
- The number of pages per minute or hits/transactions per second did not increase after the Controller ran a certain number of Vuser batches.
- All the Vusers that ran failed.
- There were no available load generators for the type of Vusers you attempted to run.

- **Transaction Response Time**

This goal tests how many Vusers can be run simultaneously without exceeding a desired transaction response time. You specify the name of the transaction in your script that you want to

test, and a minimum-maximum range of Vusers for LoadRunner to run. The transaction response time you specify should be a predefined threshold value.


For example, if you do not want a customer to wait more than five seconds to log in to your e-commerce site, specify a maximum acceptable transaction response time of five seconds. Set the minimum and maximum number of Vusers to the minimum-maximum range of customers you want to be able to serve simultaneously.

If the scenario does not reach the maximum transaction response time that you defined, your server is capable of responding within a reasonable period of time to the number of customers you want to be able to serve simultaneously. If the defined response time is reached after only a portion of the Vusers has been executed, or if you receive a message that the defined response time will be exceeded if the Controller uses the maximum number of Vusers defined, you should consider revamping your application and/or upgrading your server software and hardware.

**Notes about Transactions per Second or Transaction Response Time goals:**

- To achieve a Transactions per Second or Transaction Response Time goal, your script must contain transactions. For each of these goal types, you define the transaction in the script that you want to test.
- For a Transaction Response Time goal-oriented scenario to be effective, you must choose your transaction carefully, ensuring that it performs effective hits on the server.

## ***How to Design a Goal-Oriented Scenario***



This task describes how to design a goal-oriented scenario. In this type of scenario, you define the goals you want your test to achieve and LoadRunner automatically builds a scenario for you based on these goals.

### **1. Prerequisites**

- Before setting up the scenario, decide which goal you want the scenario to reach. For details on types of scenario goals, see "[Goals Types for Goal-Oriented Scenarios](#)" on page 1041.
- Before you start designing the scenario, record the VuGen scripts that will run in the scenario. For details, see "[How to Record a Vuser Script](#)" on page 175.

### **2. Open a new goal-oriented scenario**

- a. On the Controller toolbar, click the **New Scenario** button .

- b. In the New Scenario dialog box that opens, select **Goal-oriented Scenario**.
- c. Select scripts to run in the scenario. Select scripts in the **Available Scripts** box, and click **Add** to move them to the **Scripts in Scenario** box.


When you click **OK**, the Design tab opens and displays the new scenario.

### 3. Add load generators to the scenario

Click the **Load Generators** button . In the Load Generators dialog box that opens, click **Add** and enter the details of the load generator you are adding. For details about the Add Load Generator dialog box, see "[Add New Load Generator/Load Generator Information Dialog Box](#)" on page 1085.

### 4. Assign load generators to each script

In the Scenario Scripts pane, for each script, click the **Load Generators** column and select a load generator on which to run the script.



**Note:** By default, the script will run on all the load generators in the scenario.

### 5. Define a goal for the scenario

In the Scenario Goal pane, click the **Edit Scenario Goal** button. In the dialog box that opens, define the goal the scenario should reach. For details about filling in the scenario goal details, see "[Edit Scenario Goal Dialog Box](#)" on page 1056.

### 6. Define a location for the scenario - optional

In the Scenario Scripts pane's **Location** column, select the location for the network virtualization. This only applies if you have the network virtualization third party software installed. For details, see "[Virtual Locations Overview](#)" on page 1151.

### 7. Assign each script a percentage of the total scenario target

In the Scenario Scripts pane's **% of Target** column, enter the percentage of the total goal you want each script to reach during the scenario.

**Note:** Assign percentages to the scripts starting with the first script in the list and moving down the list.

## 8. Define service level agreements for the scenario - optional

You can define service level agreements (SLAs) to measure scenario goals over time intervals, or over a whole scenario run. When you later analyze the run using HP LoadRunner Analysis, this data is compared against the SLAs and SLA statuses are determined for the defined measurements. To define SLAs, see "[How to Define Service Level Agreements](#)" on page [1131](#).

# How to Design a Manual Scenario

This task describes how to design a manual scenario.

## 1. Prerequisites

- When designing a manual scenario, plan how you want to distribute the Vusers in the scenario. For more details, see "[Manual Scenarios](#)" on page [1040](#).
- Before you start designing the scenario, record the VuGen scripts that will run in the scenario. For details, see "[How to Record a Vuser Script](#)" on page [175](#).

## 2. Open a scenario, or create a new one

- a. On the main Controller toolbar, click the **New Scenario** button .
- b. In the New Scenario dialog box, select **Manual Scenario**.
- c. (Optional) To distribute the Vusers by percentage, select the **Use the Percentage mode...** option.

**Note:** You can convert from one scenario mode to another at any time. For details, ["How to Change the Scenario Mode \(Manual Scenario\)" on page 1047](#).

- d. (Optional) Select scripts to participate in the scenario. If you do not select the scripts here, you can select them in the step.

When you click **OK**, the scenario opens in the Design tab.

## 3. Add load generators to the scenario

Click the **Load Generators** button . In the Load Generators dialog box that opens, click **Add** and enter the details of the load generator you are adding. For details about adding load generators, see "[Add New Load Generator/Load Generator Information Dialog Box](#)" on page [1085](#).

#### 4. Add Vuser groups/scripts to the scenario

**Vuser GroupMode:** In the Scenario Groups pane, create Vuser groups to participate in the scenario. To create a group:

- a. Click the **Add Group** button .
- b. In the Add Group dialog box:
  - Give the group a name and assign a number of Vusers to the group.
  - Select a load generator on which to run the Vusers.
  - Select a Vuser script.
- c. Click the **Add Group** button  and select a Vuser script from the list.
- d. In the Scenario Scripts pane's **Load Generator** column, select load generators on which to run the scripts.
- e. When you have selected all the scripts for the scenario, in the Scenario Scripts pane's **%** column assign a percentage of the total number of Vusers to each script. Assign percentages to the scripts starting with the first script in the table and moving down the list.

**Note:** The total number of Vusers for the scenario is defined in the scenario schedule. See below.

#### 5. Define a schedule for the scenario

Define a schedule by which to run the Vusers in the scenario. For details, see "[How to Define a Schedule for the Scenario - Workflow](#)" on page [1118](#).

#### 6. Define service level agreements for the scenario - optional

You can define service level agreements (SLAs) to measure scenario goals over time intervals, or over a whole scenario run. When you later analyze the run using HP LoadRunner Analysis, this data is compared against the SLAs and SLA statuses are determined for the defined measurements. To define SLAs, see "[How to Define Service Level Agreements](#)" on page [1131](#).

## How to Change the Scenario Mode (Manual Scenario)

This task describes how to change a manual scenario from Vuser group mode to percentage mode, and vice versa.

For details about the scenario modes and the effects of changing from one to another, see "[Manual Scenarios](#)" on page 1040.

- To convert the scenario from Vuser group mode to percentage mode, select **Scenario > Convert Scenario to the Percentage Mode**.
- To convert the scenario from percentage mode to Vuser group mode, select **Scenario > Convert Scenario to the Vuser Group Mode**.

**Note:** By default, every time you convert from one mode to another, a message appears warning you that scenario and schedule settings may change. To show/hide this warning message, select **Scenario > Show Convert Scenario Mode Warning**.

## How to View/Modify Scripts in the Scenario

This section describes how to view and modify scripts used in your load test scenario.

You view/modify the details of the scripts in the Group Information dialog box (see "[Group Information Dialog Box](#)" on page 1058) or in the Script Information dialog box (see "[Script Information Dialog Box](#)" on page 1070).

### View script details

You can view the details of a script by right-clicking the script in the Scenario Groups/Scripts pane and selecting **Details**.

In the Group/Script Information dialog box that opens, you can:

- View details about the script, including:

**Note:** If you do not see some of the details listed below, click **More**.

- Script path
- Command line options
- Rendezvous points included in the script
- Vusers associated with the script
- Files associated with the script

- Open the script in VuGen by clicking the **View Script** button
- View the script's run-time settings by clicking the **Run-Time Settings** button

## Modify a script's run-time settings

- To view or modify a script's run-time settings, in the Scenario Groups/Scripts pane right-click the script and select **Run-Time Settings**.
- To view or modify run-time settings of a script associated with a particular Vuser, in the Vusers dialog box (Scenario Groups pane > **Vusers**  ) right-click the Vuser and select **Run-Time Settings**.

Modifying the run-time settings for one Vuser in a group modifies the run-time settings for all the Vusers in that group that are using the same script.

## Modify multiple scripts' run-time settings

This section describes how to modify run-time settings of multiple scripts or of a Vuser group that includes multiple scripts.

1. In the Scenario Groups/Scripts pane select multiple scripts or the Vuser group that includes multiple scripts.
2. Right-click the selection and select **Run-Time Settings**.
3. In the Multiple Run-Time Settings Mode dialog box that opens:
  - To modify run-time settings for all of the scripts simultaneously, click **Shared RTS**.
  - To modify run-time settings per script, click **Individual RTS**.

For user interface details, see "[Multiple Run-Time Settings Mode Dialog Box](#)" on page 1060.

- For details about specific run-time settings, see Run-Time Settings Overview.
- When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings.

## View/Edit a script in VuGen

To view/edit a script included in your scenario, right-click the script and select **View Script**. The script opens in VuGen. For more information on editing scripts, see the "[Debugging - Overview](#)" on page 388.

### Specify command line options

You can specify command line options to use when running a script.

1. In the Scenario Groups/Scripts pane, right-click the script and select **Details**.

2. In the Group/Script Information dialog box that opens, if **Command line** is not displayed near the bottom, click **More**.
3. Enter a command in the command line, for example: -x value -y value.

For information about passing command line argument values to a script, see "[How to Enhance a Java Script](#)" on page 673.

## View rendezvous points included in the script

1. In the Scenario Groups/Scripts pane, right-click the script and select **Details**.
2. In the Group/Script Information dialog box, if the **Rendezvous** tab is not displayed near the bottom, click **More**.

If there are rendezvous points included in the script, they are displayed in the Rendezvous tab. For details about rendezvous points, see "[Rendezvous Points Overview](#)" on page 1218.

## View Vusers associated with the script

1. In the Scenario Groups/Scripts pane, right-click the script and select **Details**.
2. In the Group/Script Information dialog box, if the **Vusers** tab is not displayed near the bottom, click **More**.

The Vusers tab displays the Vusers associated with the script.

## View files associated with the script

1. In the Scenario Groups/Scripts pane, right-click the script and select **Details**.
2. In the Group/Script Information dialog box, if the **Files** tab is not displayed near the bottom, click **More**.

By default, the Files tab lists all the files in the script's folder (only after your script has been added to the script list). These files include the configuration settings file, the init, run, and end portions of the script, the parameterization definitions file, and the .usr file. To add a file to the list, click **Add**.

### Example

To run Visual C++ Vusers on a remote load generator, you must add the .dll of the Vuser to the list of files.

You can delete the files that you add, but not the other files listed.

## Relative Paths for Scripts

You can specify a relative location for a script in your scenario. The location can be relative to the current scenario folder, or relative to the LoadRunner installation folder.

When you run a scenario, the script is automatically copied from this relative location to a temporary folder on the load generator running the script. This enables the load generator to access the script locally instead of over a network.

To specify a path relative to the current scenario director, type either of the following notations at the start of the script path:

Notation	Description
.\	Indicates that the path is relative to the location of the scenario folder
..\	Indicates that the path is relative to the location of the parent folder of the scenario folder

For example, if the current scenario is located at F:\scenarios, to specify that the script, **user1**, is located in F:\scenarios\scripts, you could type:

```
.\scripts\user1
```

To specify a path relative to the LoadRunner installation folder, type a percent sign (%) at the beginning of the script path. For example, if the LoadRunner installation folder is located at F:\LoadRunner, to specify that the script, **user1**, is located in F:\LoadRunner\scripts, you could type:

```
%\scripts\user1
```

**Note:** When specifying a relative path, you can include standard DOS notation (.\ and ..\ ) inside the path, as shown in the following example: M:\LR\my\_tests\..\..\test.usr.

## Vuser Statuses

The following table describes the possible statuses of Vusers before, during, and after a scenario run.

Status	Description
<b>Down</b>	The Vuser is down.
<b>Pending</b>	The Vuser is ready to be initialized and is waiting for an available load generator, or is transferring files to the load generator. The Vuser will run when the conditions set in its scheduling attributes are met.
<b>Initializing</b>	The Vuser is being initialized on the remote machine.

<b>Ready</b>	The Vuser already performed the init section of the script and is ready to run.
<b>Running</b>	The Vuser is running. The Vuser script is being executed on a load generator.
<b>Rendezvous</b>	The Vuser has arrived at the rendezvous point and is waiting to be released by LoadRunner.
<b>Done.Passed</b>	The Vuser has finished running. The script passed.
<b>Done.Failed</b>	The Vuser has finished running. The script failed.
<b>Error</b>	A problem occurred with the Vuser. Check the Status field on the Vuser dialog box or the output window for a complete explanation of the error.
<b>Gradual Exiting</b>	The Vuser is completing the iteration or action it is running (as defined in <b>Tools &gt; Options &gt; Run-Time Settings</b> ) before exiting.
<b>Exiting</b>	The Vuser has finished running or has been stopped, and is now exiting.
<b>Stopped</b>	The Vuser stopped when the Stop command was invoked.

## Add Group Dialog Box

This dialog box enables you to add Vuser groups to participate in a scenario.

<b>To access</b>	Manual scenario > <b>Design</b> tab > <b>Scenario Groups/Scripts</b> pane > <b>Add Group</b> 
<b>Important information</b>	While a scenario is running, you can add Vuser groups to the scenario and enable them. However, if you add a Vuser group after all the Vusers in the scenario have started running, the new group will not run in the scenario.
<b>Relevant tasks</b>	<a href="#">"How to Design a Manual Scenario" on page 1045</a>

User interface elements are described below:

UI Element	Description
 <a href="#">Browse...</a>	Enables you to add Vuser scripts to the list of scripts.
 <a href="#">Record...</a>	Opens VuGen where you can record a Vuser script. For more information on recording Vuser scripts, see <a href="#">"How to Record a Vuser Script" on page 175</a> .
<b>Group Name</b>	<p>The name of the Vuser group.</p> <p>When you select a script the Vuser group is automatically given the same name as the script. You can modify the group name.</p> <p><b>Note:</b> The name is limited to a maximum of 55 characters.</p>

<b>Load Generator Name</b>	The load generator assigned to the Vuser group. To add a load generator to this list, select <b>Add</b> from the list. For user interface details, see " <a href="#">Add New Load Generator/Load Generator Information Dialog Box</a> " on page 1085.
<b>Select Script</b>	Lists the available scripts that have been added to the scenario. When you select a script, its name and path are displayed above the list. To display the scripts with their full paths, right-click the list area and select <b>Show Paths</b> . <b>Note:</b> If a script uses Unique file parameterization, running more than one Vuser group with that script in the same scenario may cause unexpected scenario results. For more information about Unique file parameterization, see " <a href="#">Data Assignment Methods for File/Table/XML Parameters</a> " on page 413.
<b>Vuser Quantity</b>	The number of Vusers to add to the group.

## Add Script Dialog Box

This dialog box enables you to add Vuser scripts to a scenario.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>All scenarios: <b>Design</b> tab &gt; Right-click in <b>Scenario Scripts</b> pane &gt; <b>Add Script</b></li><li>Goal-oriented scenario: <b>Design</b> tab &gt; <b>Scenario Scripts</b> pane &gt; <b>Add Script</b></li><li>Manual scenario (percentage mode): <b>Design</b> tab &gt; <b>Add Group</b> </li></ul>
<b>Important information</b>	While a scenario is running, you can add scripts to the scenario and enable them. However, if you add a script after all the Vusers in the scenario have started running, the added script will not run in the scenario.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li><a href="#">"How to Design a Manual Scenario" on page 1045</a></li><li><a href="#">"How to Design a Goal-Oriented Scenario" on page 1043</a></li></ul>

User interface elements are described below:

UI Element	Description
 <a href="#">Browse...</a>	Enables you to add Vuser scripts to the list of scripts.
 <a href="#">Record...</a>	Opens VuGen where you can record a Vuser script. For more information on recording Vuser scripts, see " <a href="#">How to Record a Vuser Script</a> " on page 175.

UI Element	Description
Select Script	Lists the scripts available for the scenario. When you select a script, its name and path are displayed above the list. To display the scripts with their full paths, right-click the list area and select <b>Show Paths</b> .

## Add Vusers Dialog Box

This dialog box enables you to add Vusers to a Vuser group.

To access	Design tab > Scenario Groups pane > Vusers  > Add Vusers
Important information	<ul style="list-style-type: none"><li>• Relevant for manual scenarios in Vuser group mode only.</li><li>• Available when a group is selected in the Scenario Groups pane.</li></ul>
See also	<a href="#">"Run/Stop Vusers Dialog Box" on page 1210</a>

User interface elements are described below:


UI Element	Description
 Browse...	Enables you to add Vuser scripts to the list of scripts. <b>Note:</b> To add a VB Vuser script, select the .usr file.
 Record...	Opens VuGen where you can record a Vuser script. For more information on recording Vuser scripts, see <a href="#">"How to Record a Vuser Script" on page 175</a> .
 Run-Time Settings...	Opens the Run-Time Settings dialog box, where you can edit the script's run-time settings. When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings.
 Parameter list...	Opens the Parameter list in VuGen where you can create, view, modify, and delete script parameters. For details, see <a href="#">"Parameterizing - Overview" on page 408</a> .
<b>Group Name</b>	The name of the group to which to add Vusers.
<b>Load Generator Name</b>	The load generator assigned to the Vuser group. To add a load generator to this list, select <b>Add</b> from the list. For user interface details, see <a href="#">"Add New Load Generator/Load Generator Information Dialog Box" on page 1085</a> .
<b>Quantity to add</b>	The number of Vusers to add to the Vuser group.
<b>Select Script</b>	Lists the scripts available for the scenario. When you select a script, its name and path are displayed above the list. To display the scripts with their full paths, right-click the list area and select <b>Show Paths</b> .



## Design Tab



The Design tab enables you to design load test scenarios.

To access	Design tab
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Design a Manual Scenario" on page 1045</li><li>"How to Design a Goal-Oriented Scenario" on page 1043</li><li>"How to Define a Schedule for the Scenario - Workflow" on page 1118</li><li>"How to Define Service Level Agreements" on page 1131</li><li>"How to Change the Scenario Mode (Manual Scenario)" on page 1047</li><li>"How to View/Modify Scripts in the Scenario" on page 1047</li></ul>

User interface elements are described below:

UI Element	Description
<b>Scenario Goal pane</b> (Goal-oriented scenario)	In goal-oriented scenarios, displays information regarding the scenario goal.  <p>For user interface details, see "Scenario Goal Pane" on page 1063.</p>

UI Element	Description																
<b>Scenario Groups pane</b> (Manual scenario in Vuser Group mode)	<p>Displays the Vuser groups created for the scenario.</p>  <table border="1"> <thead> <tr> <th>Group Name</th> <th>Script Path</th> <th>Quantity</th> <th>Load Gen.</th> </tr> </thead> <tbody> <tr> <td>demo_script</td> <td>C:\...\Tutorial\demo_script</td> <td>10</td> <td>localhost</td> </tr> <tr> <td>debuggingexample3</td> <td>C:\...\DebuggingExample3</td> <td>1</td> <td>localhost</td> </tr> <tr> <td>basic_script</td> <td>C:\...\Tutorial\basic_script</td> <td>10</td> <td>localhost</td> </tr> </tbody> </table>	Group Name	Script Path	Quantity	Load Gen.	demo_script	C:\...\Tutorial\demo_script	10	localhost	debuggingexample3	C:\...\DebuggingExample3	1	localhost	basic_script	C:\...\Tutorial\basic_script	10	localhost
Group Name	Script Path	Quantity	Load Gen.														
demo_script	C:\...\Tutorial\demo_script	10	localhost														
debuggingexample3	C:\...\DebuggingExample3	1	localhost														
basic_script	C:\...\Tutorial\basic_script	10	localhost														
<b>Scenario Schedule pane</b> (Manual scenario)	<p>Displays the scenario schedule.</p>  <p>Schedule Name: Schedule 1</p> <p>Schedule by: <input checked="" type="radio"/> Scenario <input type="radio"/> Group</p> <p>Run Mode: <input checked="" type="radio"/> Real-world schedule <input type="radio"/> Basic schedule</p> <p>Global Schedule</p> <p>Total: 21 Vusers</p> <p>Interactive Schedule Graph</p>																

UI Element	Description
<b>Scenario Scripts pane</b>	<p>Displays the Vuser scripts selected for the scenario.</p>  <p>For user interface details:</p> <ul style="list-style-type: none"> <li>See "Scenario Groups/Scripts Pane - Manual Scenarios" on page 1064.</li> <li>See "Scenario Scripts Pane - Goal-Oriented Scenarios" on page 1067.</li> </ul>
<b>Service Level Agreement pane</b>	<p>Lists the service level agreements defined for the scenario.</p>  <p>For user interface details, see "Service Level Agreement Pane" on page 1135.</p>

## Edit Scenario Goal Dialog Box

This dialog box enables you to set goals for your scenario.

<b>To access</b>	Goal-oriented scenario > <b>Design</b> tab > <b>Scenario Goal</b> pane > <b>Edit Scenario Goal</b>
<b>Important information</b>	<ul style="list-style-type: none"> <li>Available for goal-oriented scenarios only.</li> <li>When you run a goal-oriented scenario, the goal you defined is displayed in the appropriate graph, along with the scenario results. This enables you to compare the results with your target goal.</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Design a Goal-Oriented Scenario" on page 1043</a>

User interface elements are described below:

UI Element	Description
	Enables you to rename the selected goal profile.
	Enables you to delete the selected goal profile.
	Enables you to define a new goal profile.
	<p>Opens the Scenario Start dialog box where you can set the scenario start time as follows:</p> <ul style="list-style-type: none"> <li><b>Without delay.</b> As soon as the Start Scenario command is issued.</li> <li><b>With a delay of HH:MM:SS.</b> The specified time after the Start Scenario command is issued.</li> <li><b>At HH:MM:SS on &lt;date&gt;.</b> At a specified time on a specified date.</li> </ul>
<b>Define Scenario Goal</b>	<p>The scenario goal:</p> <ul style="list-style-type: none"> <li><b>Goal Type.</b> The type of goal. For more details, see <a href="#">"Goals Types for Goal-Oriented Scenarios" on page 1041</a>.</li> <li><b>Transaction Name.</b> (When goal type is <b>Transactions per second/Transaction Response Time</b>) The static script transaction for your scenario to test, or the name of an automatic/dynamic script transaction that you have recorded.</li> <li><b>Reach Goal of &lt;value&gt; &lt;goal type&gt;.</b> The desired goal limits.</li> <li><b>Using a minimum of &lt;value&gt; and a maximum of &lt;value&gt; Vusers.</b> The minimum and maximum number of Vusers to use in the scenario.</li> </ul>

<b>Do not change recorded think time</b>	If selected, LoadRunner runs the scenario using the think time recorded in the script. <b>Note:</b> If you select this option, you may need to increase the number of Vusers in your scenario in order to reach your target.
<b>Goal Profile Name</b>	The goal profile name.
<b>Load Behavior tab</b>	Enables you to specify how and when the Controller should reach the target. <b>Ramp Up.</b> How the Vusers should start running. <ul style="list-style-type: none"> <li>• <b>Automatic.</b> The Controller starts running the default number of Vusers in a batch, that is, 50 Vusers every two minutes. If the maximum number of Vusers defined is less than 50, then it runs all the Vusers.</li> <li>• <b>Reach target X after.</b> The amount of scenario time after which Controller should reach the target.</li> <li>• <b>Step up by.</b> How rate at which the Controller should reach the target (x number of Vusers/hits/pages every x amount of time). (Not available for the Transactions per Second and Transaction Response Time goal types.)</li> </ul>
<b>Load Preview graph</b>	A graphical representation of the goal and load behavior defined for the scenario.
<b>Scenario Settings tab</b>	Enables you to specify the actions to take when the target is reached, or if the target is not reached: <ul style="list-style-type: none"> <li>• <b>Run Time.</b> The amount of time (in hours, minutes, and seconds) to run the scenario after the target has been reached.</li> <li>• <b>If target cannot be reached.</b> The action to be taken if the target cannot be reached.</li> <li>▪ <b>Receive Notification.</b> If selected, the Controller sends an error message indicating that the target could not be reached.</li> </ul>


## Group Information Dialog Box

This dialog box displays details about the selected Vuser group, and enables you to modify the group's settings.

<b>To access</b>	Manual Scenario > Design tab > <b>Scenario Groups</b> pane > <b>Details</b> 
------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	<ul style="list-style-type: none"> <li>• Relevant for manual scenarios in Vuser group mode only.</li> <li>• Available when a group is selected in the Scenario Groups pane.</li> </ul>
<b>Relevant Tasks</b>	<ul style="list-style-type: none"> <li>• <a href="#">"How to Design a Manual Scenario" on page 1045</a></li> <li>• <a href="#">"How to View/Modify Scripts in the Scenario" on page 1047</a></li> </ul>

User interface elements are described below:

UI Element	Description
 Refresh ▾	<p>Updates script settings as follows:</p> <ul style="list-style-type: none"> <li>• <b>Script.</b> If a script was modified during a scenario run, updates the script details in the scenario.</li> <li>• <b>Run-Time Settings.</b> If you modified a script's run-time settings from the Controller, restores the initial run-time settings.</li> </ul>
 View Script...	<p>Opens VuGen where you can view and edit the script. For more information on editing scripts, see <a href="#">"Enhancing a Script for Load Testing - Overview" on page 395</a>.</p>
 Run-Time Settings...	<p>Opens the Run-Time Settings dialog box, where you can edit the Vuser script's run-time settings. When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings. To restore the initial settings previously set using VuGen, click the <b>Refresh</b> button and select <b>Run-Time Settings</b>.</p>
<b>Command Line</b>	<p>The command line options to use when running the script. <b>Example:</b> <code>-x value -y value</code>. For information about passing command line argument values to a script, see <a href="#">"How to Enhance a Java Script" on page 673</a>.</p>
<b>Files tab</b>	<p>Displays all files used by the script, including the configuration settings file, the init, run, and end portions of the script, the parameterization definitions file, and the <b>.usr</b> file.</p> <ul style="list-style-type: none"> <li>• To exclude a file from the list, clear the check box adjacent to it.</li> <li>• To add a file or folder used by the script, click the <b>Add</b> button.</li> </ul> <p><b>Note:</b> To run Visual C++ Vusers on a remote load generator, you must add the <b>.dll</b> of the Vuser to this list.</p> <ul style="list-style-type: none"> <li>• You can delete the files that you add, but not the other files listed.</li> </ul>
<b>Group Name</b>	<p>The name of the Vuser group. To modify, type a new name in the <b>Group Name</b> box. The name is limited to a maximum of 55 characters.</p>

UI Element	Description
<b>Load Generator Name</b>	The load generator assigned to the Vuser group. To add a load generator to this list, select <b>Add</b> from the list. For user interface details, see " <a href="#">Add New Load Generator/Load Generator Information Dialog Box</a> " on page 1085.
<b>Rendezvous tab</b>	Displays the rendezvous points defined for the selected script.
<b>Script</b>	The name, path, and type of the Vuser script selected for the Vuser group.
<b>Vusers tab</b>	Displays all Vusers associated with the selected script.

## **Multiple Run-Time Settings Mode Dialog Box**

This dialog box enables you to select the mode for modifying run-time settings of multiple selected scripts.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• In the Scenario Groups/Scripts pane, right-click a multiple selection of scripts, and select <b>Run-Time Settings</b></li><li>• Right-click a Vuser group that includes multiple scripts and select <b>Run-Time Settings</b></li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>• If one of the selected scripts does not support shared run-time settings, then you will only have the option of modifying each script's individual run-time settings (<b>Individual RTS</b>).</li><li>• <b>Shared RTS</b> mode is disabled for GUI or Astra LoadTest Vusers.</li><li>• Some run-time settings cannot be modified in <b>Shared RTS</b> mode. These settings will not appear in the Run-Time Settings window. To modify them, open the run-time settings for each individual script.</li></ul> <p>The following nodes will not appear in Shared RTS mode:</p> <ul style="list-style-type: none"><li>▪ <b>Run Logic</b> node - for protocols which support the <b>Run Logic</b> node, the <b>Iterations</b> box appears in the <b>Pacing</b> node</li><li>▪ <b>Additional Attributes</b> node</li><li>▪ <b>Internet Protocol:ContentCheck</b> node</li><li>▪ <b>Java Environment Settings:Classpath</b> node</li><li>▪ Nodes with tables in the format <b>Property, Value</b> for the protocols: Citrix ICA, Oracle NCA, and WAP For example: <b>Oracle NCA:Client Emulation</b> node</li></ul>

#### Relevant tasks

"How to View/Modify Scripts in the Scenario" on page 1047

User interface elements are described below:


UI Element	Description
Individual RTS	Opens a separate Run-Time Settings dialog box (one at a time) for each selected script. In this mode, you modify each script's settings individually.
Shared RTS	Opens the Run-Time Settings Shared Mode dialog box containing all of the run-time settings in blank mode. In this mode, any settings that are changed are applied to all selected scripts. All other run-time settings remain unchanged. See <b>Important information</b> above.


## New Scenario Dialog Box

This dialog box enables you to create a new scenario and select Vuser scripts or test modules to run in the scenario.

To access	Controller toolbar > <b>New Scenario</b> 
Important information	Before you create a scenario, you should have a good idea as to the type of scenario you want to create. See "LoadRunner Controller Overview" on page 1013.
Relevant tasks	<ul style="list-style-type: none"><li>"How to Design a Manual Scenario" on page 1045</li><li>"How to Design a Goal-Oriented Scenario" on page 1043</li></ul>

User interface elements are described below:

UI Element	Description
 <u>Add ==&gt;</u>	Moves the selected item in the <b>Available Scripts/Modules</b> box to the <b>Scripts/Modules in Scenario</b> box.
 <u>Remove</u>	Removes the selected script or module from the <b>Scripts/Modules in Scenario</b> box.
 <u>Browse...</u>	Enables you to add items to the list of available scripts or unit tests. Scripts have a <b>.usr</b> extension, while unit tests can have a <b>.dll</b> , <b>.jar</b> , or <b>.class</b> extension.
 <u>Record...</u>	Opens VuGen so that you can record a Vuser script. For details, see "How to Record a Vuser Script" on page 175.

	Opens the Connection to HP ALM dialog box, where you can connect to Application Lifecycle Management to download scripts. For details, see <a href="#">"Managing Scenarios Using Application Lifecycle Management - Overview" on page 1229</a> .
<b>Select Scenario Type</b>	<p>Select the type of scenario to create. For details, see <a href="#">"LoadRunner Controller Overview" on page 1013</a>.</p> <ul style="list-style-type: none"><li>• <b>Manual Scenario.</b> You manually build the scenario creating Vuser groups and specifying the script, load generators, and the number of Vusers to include in each Vuser group.</li><li>▪ <b>Use the Percentage mode...</b> You define the total number of Vusers to be used in the scenario and assign a percentage of the total number of Vusers to each Vuser script.</li></ul> <p><b>Note:</b> You can convert from one scenario mode to another at any time. For details, see <a href="#">"How to Change the Scenario Mode (Manual Scenario)" on page 1047</a>.</p> <ul style="list-style-type: none"><li>• <b>Goal-Oriented Scenario.</b> You define the goals you want your test to achieve, and LoadRunner automatically builds a scenario for you, based on these goals.</li></ul>
<b>Test Scripts/ Test Modules</b>	<p>The type of test to use in the scenario:</p> <ul style="list-style-type: none"><li>• <b>LoadRunner Scripts.</b> LoadRunner Vuser scripts created with VuGen.</li><li>• <b>System or Unit Tests.</b> NUnit, JUnit, or Selenium test modules created within an external application, such as Visual Studio or Eclipse. These must be files with <b>.dll</b>, <b>.jar</b>, or <b>.class</b> extensions.</li></ul> <p>The <b>Browse</b> button allows you to locate the appropriate type of test.</p>

<b>Select the script(s) you would like to use in your scenario</b>	<p>(Optional) Select the scripts to use in the scenario.</p> <ul style="list-style-type: none"> <li><b>Available Scripts/Modules.</b> Lists the fifty most recently used items.</li> <li><b>Scripts/Modules in Scenario.</b> Lists the items selected for the scenario.</li> </ul> <p>Click <b>Add/Remove</b> to move selected items between the two lists.</p> <p><b>Note:</b> You can change the maximum number of scripts or modules displayed in the <b>Available Scripts/Modules</b> box by modifying the following registry key:</p> <ul style="list-style-type: none"> <li>For scripts: <b>HKEY_CURRENT_USER\Software\Mercury Interactive\RecentScripts\max_num_of_scripts</b></li> <li>For system and unit tests: <b>HKEY_CURRENT_USER\Software\Mercury Interactive\RecentModules\max_num_of_scripts</b></li> </ul>
<b>Show at startup</b>	<p>When selected, the New Scenario dialog box is displayed upon opening the Controller.</p> <p><b>Note:</b> This option can also be enabled/disabled from the Controller's View menu. Select <b>View &gt; Show New Scenario Dialog</b>.</p>

## Scenario Goal Pane

This pane displays the goals defined for the scenario.

<b>To access</b>	Goal-oriented scenario > <b>Design</b> tab
<b>Important information</b>	<ul style="list-style-type: none"> <li>Available for goal-oriented scenarios only.</li> <li>The goal profiles include the type of goal, the minimum and maximum number of Vusers that should be used in the scenario, the duration of the scenario, and the load behavior.</li> </ul>
<b>Relevant tasks</b>	<a href="#">"How to Design a Goal-Oriented Scenario" on page 1043</a>

User interface elements are described below:

UI Element	Description
 <a href="#">Edit Scenario Goal...</a>	Opens the Edit Scenario Goal dialog box, where you set the goals for the scenario. See <a href="#">"Edit Scenario Goal Dialog Box" on page 1056</a> .
<b>Goal</b>	The defined goal, including the type of goal and the expected target.
<b>Goal Profile Name</b>	The name of the goal profile.

<b>Load Behavior</b>	How and when the Controller should reach the defined goal.
<b>Load Preview graph</b>	A graphical representation of the goal and load behavior defined for the scenario.
<b>Max Number of Vusers</b>	The maximum number of Vuser to run in the scenario.
<b>Min Number of Vusers</b>	The minimum number of Vuser to run in the scenario.
<b>Scenario Duration</b>	The amount of time the scenario should continue running after reaching the defined goal.

## Scenario Groups/Scripts Pane - Manual Scenarios


This pane displays the Vuser groups/scripts that were added to the scenario.

<b>To access</b>	Manual Scenario > <b>Design</b> tab
<b>Important information</b>	<p>The Design tab displays the <b>Scenario Groups</b> pane where you can define Vuser groups to run Vuser scripts in a scenario. It lists all Vuser groups, together with the script or module path, and the load generators. You define the number of Vusers per group in one of two ways:</p> <ul style="list-style-type: none"> <li><b>Vuser group mode.</b> The actual number of Vusers assigned to the group. (default).</li> <li><b>Percentage mode:</b> The percentage of the total number of Vusers, assigned to the group.</li> </ul> <p><b>Note:</b> You can change from one scenario mode to another at any time. For details, see "<a href="#">How to Change the Scenario Mode (Manual Scenario)</a>" on page 1047.</p>
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li><a href="#">"How to Design a Manual Scenario"</a> on page 1045</li> <li><a href="#">"How to Change the Scenario Mode (Manual Scenario)"</a> on page 1047</li> </ul>
<b>See also</b>	<a href="#">"LoadRunner Controller Overview"</a> on page 1013

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Start Scenario.</b> Starts running the scenario.
	<b>Virtual Users.</b> Opens the Vusers dialog box where you can define properties for individual Vusers within a group. You can assign a different script/module and load generator to each Vuser. For user interface details, see " <a href="#">"Vusers Dialog Box"</a> on page 1072.

UI Element	Description
	<b>Add Group.</b> <ul style="list-style-type: none"><li>• <b>Vuser group mode:</b> Opens the Add Group dialog box where you create Vuser groups for the scenario. See "<a href="#">Add Group Dialog Box</a>" on page <a href="#">1051</a>.</li><li>• <b>Percentage mode:</b> Opens the Add Script dialog box where you select Vuser scripts for the scenario. See "<a href="#">Add Script Dialog Box</a>" on page <a href="#">1052</a>.</li></ul>
	<b>Remove Group.</b> Deletes the selected Vuser group/script.
	<b>Run-Time Settings.</b> Opens the Run-Time Settings dialog box. <ul style="list-style-type: none"><li>• When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings. To restore the initial settings that were assigned in VuGen, click the <b>Refresh</b> button and select <b>Run-Time Settings</b>.</li><li>• If run-time settings were not defined in VuGen for the current script, the Controller uses default settings for Log and Think Time. Default VuGen settings are displayed for all other nodes.</li></ul>
	<b>Details.</b> Opens the Group/Script Information dialog box where you can view and modify the Vuser group/script's settings. For details, see " <a href="#">Group Information Dialog Box</a> " on page <a href="#">1058</a> or " <a href="#">Script Information Dialog Box</a> " on page <a href="#">1070</a> .
	<b>View Script.</b> Opens the script in VuGen where you can view and edit the Vuser script. For more information on editing scripts, see " <a href="#">Enhancing a Script for Load Testing - Overview</a> " on page <a href="#">395</a> .
	<b>Service Virtualization.</b> Opens the Service Virtualization dialog box. For more information, see the <i>HP Service Virtualization User Guide</i> .

UI Element	Description
<b>&lt;Groups/Scripts table&gt;</b>	<p>Displays the following information about the Vuser groups/scripts selected for the scenario:</p> <ul style="list-style-type: none"> <li>• <input checked="" type="checkbox"/> . Indicates that the Vuser group/script is participating in the scenario.</li> <li>• <b>Group/Script Name.</b> The name of the Vuser group/script.</li> <li>• <b>Script Path.</b> The path of the Vuser script. An icon adjacent to the path, indicates whether the entry is a Vuser script , a unit test module , such as .NET or Java, or a UFT/QTP test .</li> </ul> <p>If the Vuser group includes more than one script, the scripts' names are listed. Clicking the cell's drop-down arrow displays the scripts' full paths.</p>  <p>If you want to access the script from a location that is relative to the current scenario folder, you can replace the actual path with the relative path. For details, see "<a href="#">"Relative Paths for Scripts" on page 1050</a>.</p> <ul style="list-style-type: none"> <li>• <b>Virtual Location.</b> A drop-down list of all available network virtualization locations for the group. To run this group without network virtualization, do not select a location. <b>Note:</b> This list is only available when the Shunra Network Virtualization software is installed and enabled per group (not per load generator). If you have it installed, but you have not enabled it, the column value is grayed out. To enable network virtualization or edit the locations, see "<a href="#">"Network Virtualization Settings Dialog Box" on page 1155</a>.</li> <li>• <b>Quantity.</b> (Vuser group mode) The number of Vusers assigned to the Vuser group. This column is read-only when the defining a real-world schedule (default schedule). In this case, the quantity of Vusers is defined when designing the scenario schedule.</li> <li>• <b>%.</b> (Percentage mode) The percentage of Vusers assigned to run the Vuser script. If you modify the percentage assigned to one group, the percentages assigned to the other scripts change to create a total of 100% for all of the Vuser scripts. <b>Note:</b> Modify percentages to the scripts starting with the first script in the</li> </ul>





UI Element	Description
	<p>list and moving down the list.</p> <ul style="list-style-type: none"> <li><b>Load Generators.</b> The load generators assigned to the Vuser group/script.</li> </ul> <p>If you select multiple load generators for a group/script, the Vusers assigned to the Vuser group/script are distributed evenly among the load generators.</p> <p><b>Default value (in percentage mode):</b> All Load Generators</p> <p><b>Note:</b> To add a load generator to this list, select <b>Add</b> from the list. For more details, see "<a href="#">Add New Load Generator/Load Generator Information Dialog Box</a>" on page 1085.</p>
<b>&lt;Groups/Scripts table&gt;</b> (continued)	<ul style="list-style-type: none"> <li><b>Load Generators.</b> The load generators assigned to the Vuser group/script.</li> </ul> <p>If you select multiple load generators for a group/script, the Vusers assigned to the Vuser group/script are distributed evenly among the load generators.</p> <p><b>Default value (in percentage mode):</b> All Load Generators</p> <p><b>Note:</b> To add a load generator to this list, select <b>Add</b> from the list. For more details, see "<a href="#">Add New Load Generator/Load Generator Information Dialog Box</a>" on page 1085.</p>
<b>&lt;Right-click menu&gt;</b>	<ul style="list-style-type: none"> <li><b>Auto Sort.</b> When adding a Vuser group/script, automatically sorts the table according to the defined sort.</li> <li><b>Sort Groups/Scripts.</b> Enables you to sort the table by Vuser group/script name, script path, quantity/percentage of Vusers, or load generator. To sort the table in ascending/descending order, click the relevant table heading.</li> </ul>

## Scenario Scripts Pane - Goal-Oriented Scenarios

This pane lists the Vuser scripts selected for the goal-oriented scenario.

<b>To access</b>	Goal-oriented scenario > <b>Design</b> tab
<b>Relevant tasks</b>	<a href="#">"How to Design a Goal-Oriented Scenario" on page 1043</a>
<b>See also</b>	<a href="#">"LoadRunner Controller Overview" on page 1013</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 <a href="#">Start Scenario</a>	Starts running the scenario.
 <a href="#">Generators...</a>	Opens the Load Generators dialog box where you can add new load generators and view details about existing load generators. See " <a href="#">Load Generators Dialog Box</a> " on page 1101.
 <a href="#">Add Script...</a>	Opens the Add Script dialog box where you can select Vuser scripts to add to the scenario. See " <a href="#">Add Script Dialog Box</a> " on page 1052.
 <a href="#">Remove</a>	Deletes the selected Vuser script.
 <a href="#">Run-Time Settings...</a>	Opens the Run-Time Settings dialog box, where you can edit the Vuser script's run-time settings. <b>Notes:</b> <ul style="list-style-type: none"><li>When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings.</li><li>If run-time settings for a script were not defined in VuGen, the Controller displays its own default settings for Log and Think Time. Default VuGen settings are displayed for all other nodes.</li></ul>
 <a href="#">Details...</a>	Opens the Script Information dialog box where you can view the Vuser script's settings. See " <a href="#">Script Information Dialog Box</a> " on page 1070.
 <a href="#">View Script...</a>	Opens the script in VuGen where you can view and edit the Vuser script. For more information on editing scripts, see " <a href="#">Scripting Options</a> " on page 103.
<Right-click menu>	<ul style="list-style-type: none"><li><b>Auto Sort.</b> When adding a script, automatically sorts the table according to the defined sort.</li><li><b>Sort Scripts.</b> Enables you to sort the table by Vuser script name, script path, percentage of Vusers, or load generator. To sort the table in ascending/descending order, click the relevant table heading.</li></ul>

UI Element	Description
<Scripts table>	<p>Displays the following information about the Vuser scripts selected for the scenario:</p> <ul style="list-style-type: none"><li>• <input checked="" type="checkbox"/> . Indicates that the script is participating in the scenario.</li><li>• <b>Script Name.</b> The name of the Vuser script.</li><li>• <b>Script Path.</b> The path of the Vuser script. If you want to access the script from a location that is relative to the current scenario folder, you can replace the actual path with the relative path. For details, see <a href="#">"Relative Paths for Scripts" on page 1050</a>.</li><li>• <b>% of Target.</b> The percentage of the overall target number of Vusers, pages per minute, hits per second, transactions per second, or transaction response time that is automatically distributed to each Vuser script.</li><li>• <b>Load Generators.</b> The load generators assigned to the script. If you select multiple load generators for a script, the Vusers assigned to the script are distributed evenly among the load generators.</li></ul> <p><b>Default value:</b> All Load Generators</p> <p><b>Note:</b> To add a load generator to this list, select <b>Add</b> from the list. For more details, see <a href="#">"Add New Load Generator/Load Generator Information Dialog Box" on page 1085</a>.</p>

## Scenario Start Time Dialog Box

This dialog box enables you to set when the scenario will start.

To access	Goal-oriented scenario > <b>Design tab</b> > <b>Scenario Schedule</b> pane > <b>Scenario Start Time</b> button.
-----------	-----------------------------------------------------------------------------------------------------------------

User interface elements are described below:


UI Element	Description
Without delay	Starts the scenario as soon as the Start Scenario command is issued.
With a delay of HH:MM:SS	Starts the scenario the specified time after the Start Scenario command is issued.
At HH:MM:SS on <date>	Starts the scenario at a specified time on a specified date.


## Script Information Dialog Box

This dialog box displays details about the selected Vuser group, and enables you to modify the group's settings.

To access	Design tab > Scenario Scripts pane > Details 
<b>Important information</b>	Available when a script is selected in the Scenario Scripts pane. Relevant to: <ul style="list-style-type: none"><li>• Manual scenarios in percentage mode</li><li>• Goal-oriented scenarios</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">"How to View/Modify Scripts in the Scenario" on page 1047</a></li></ul>

User interface elements are described below:

UI Element	Description
 Refresh ▾	Updates script settings as follows: <ul style="list-style-type: none"><li>• <b>Script.</b> If the script was modified during a scenario run, updates the script details in the scenario.</li><li>• <b>Run-Time Settings.</b> If you modified the run-time settings from the Controller, restores the initial run-time settings.</li></ul>
 View Script...	Opens VuGen where you can view and edit the script. For more information on editing scripts, see " <a href="#">"Enhancing a Script for Load Testing - Overview" on page 395</a> . <b>Note:</b> If you use VuGen to make changes to a script while the Controller is running, click <b>Refresh</b> and select <b>Script</b> to update the script details in the scenario.
 Run-Time Settings...	Opens the Run-Time Settings dialog box, where you can edit the Vuser script's run-time settings. <b>Notes:</b> <ul style="list-style-type: none"><li>• When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings. To restore the initial settings previously set using VuGen, click the <b>Refresh</b> button and select <b>Run-Time Settings</b>.</li><li>• If run-time settings for a script were not defined in VuGen, the Controller displays its own default settings for Log and Think Time. Default VuGen settings are displayed for all other nodes.</li></ul>

UI Element	Description
 Network Virtualize...	Opens the "Network Virtualization Settings Dialog Box" on page 1155. This dialog box lets you enable Network Virtualization, or change the working mode ( <b>Per Group</b> or <b>Per Load Generator</b> ). It also provides a link to the Shunra screens, allowing you to configure the virtualization properties.
<b>Command Line</b>	The command line options to use when running the script. <b>Example:</b> -x value -y value. For information about passing command line argument values to a script, see "How to Enhance a Java Script" on page 673.
<b>Files tab</b>	Displays all files used by the script, including the configuration settings file, the init, run, and end portions of the script, the parameterization definitions file, and the .usr file. <ul style="list-style-type: none"> <li>• To exclude a file from the list, clear the check box adjacent to it.</li> <li>• To add a file or folder used by the script, click the <b>Add</b> button.</li> </ul> <b>Note:</b> To run Visual C++ Vusers on a remote load generator, you must add the .dll of the Vuser to this list. <ul style="list-style-type: none"> <li>• You can delete the files that you add, but not the other files listed.</li> </ul>
<b>Rendezvous tab</b>	Displays the rendezvous points defined for the selected script.
<b>Script</b>	The name, path, and type of the selected Vuser script.
<b>Vusers tab</b>	Displays all Vusers associated with the selected script.

## Vuser Information Dialog Box

This dialog box displays details about a specific Vuser in a group, and lets you modify the load generator and script settings for the Vuser.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"> <li>• Manual scenario &gt; <b>Design</b> tab &gt; <b>Scenario Groups</b> pane &gt; <b>Vusers</b>  &gt; </li> <li>• In Vusers dialog box, double-click Vuser.</li> </ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>• "How to View/Modify Scripts in the Scenario" on page 1047</li> <li>• "How to Run a Scenario" on page 1191</li> </ul>

User interface elements are described below:

UI Element	Description
 <a href="#">Browse...</a>	Enables you to add Vuser scripts to the list of scripts. <b>Note:</b> To add a VB Vuser script, select the <b>.usr</b> file.
 <a href="#">Record...</a>	Opens VuGen where you can record a Vuser script. For more information on recording Vuser scripts, see " <a href="#">How to Record a Vuser Script</a> " on page 175.
 <a href="#">Run-Time Settings...</a>	<p>Opens the Run-Time Settings dialog box, where you can edit the Vuser script's run-time settings.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>Modifying the run-time settings for one Vuser modifies the run-time settings for all the Vusers in the group that are using the same script.</li> <li>When you modify the run-time settings from the Controller, LoadRunner runs the script using the modified settings.</li> <li>If run-time settings for a script were not defined in VuGen, the Controller displays its own default settings for Log and Think Time. Default VuGen settings are displayed for all other nodes.</li> </ul>
 <a href="#">Parameter list...</a>	Opens the Parameter list in VuGen where you can create, view, modify, and delete Vuser script parameters. For details, see " <a href="#">Parameterizing - Overview</a> " on page 408.
<b>Group Name</b>	The name of the group to which the selected Vuser belongs.
<b>Load Generator Name</b>	The load generator assigned to the Vuser's Vuser group. To add a load generator to this list, select <b>Add</b> from the list. For user interface details, see " <a href="#">Add New Load Generator/Load Generator Information Dialog Box</a> " on page 1085.
<b>Select Script</b>	Lists the available scripts that have been added to the scenario. When you select a script, its name and path are displayed above the list. To display the scripts with their full paths, right-click the list area and select <b>Show Paths</b> .
<b>Vuser Name</b>	The name of the selected Vuser.

## Vusers Dialog Box

This dialog box displays the status of the Vusers in the selected Vuser group.

<b>To access</b>	Manual scenario > <b>Design</b> tab > <b>Scenario Groups</b> pane > <b>Vusers</b> 
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li><a href="#">"How to Run a Scenario"</a> on page 1191</li> <li><a href="#">"Control Vusers During a Scenario Run - Use-Case Scenario"</a> on page 1194</li> </ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 <b>Show Vuser Log.</b>	Displays a log containing run-time information about the Vuser that is refreshed, by default, every 1000 milliseconds. For more information, see " <a href="#">"Vuser Script Log" on page 1216</a> ".
 <b>Hide Vuser Log.</b>	Closes the Vuser log.
 <b>Run</b>	Starts running the selected Vuser.
 <b>Gradual Stop</b>	Instructs the Controller to complete the current iteration or action before stopping the Vuser. <b>Note:</b> This option is only available when the Vuser is in the <b>Run</b> state, and if you selected the <b>Wait for the current iteration to end before exiting</b> or <b>Wait for the current action to end before exiting</b> option in the Run-Time Settings tab of the Options dialog box.
 <b>Stop</b>	Stops running the selected Vuser immediately.
 <b>Reset</b>	Resets the status of the Vuser to Down.
 <b>Details...</b>	Opens the Vuser Information dialog box, where you can view details about the selected Vuser.
 <b>Add Vuser(s)...</b>	Opens the Add Vusers dialog box where you can add more Vusers to the Vuser group.
 <b>Refresh</b>	Refreshes the contents of the columns in the Vuser list. This is relevant when you make changes outside of this window. The changes may be in the group or test information or, when working with network virtualization, updating the virtual location.
<b>&lt;Filter by script&gt;</b>	Filters the Vusers table by the selected script.
<b>&lt;Filter by status&gt;</b>	Filters the Vusers table by the selected Vuser status. For details, see " <a href="#">"Vuser Statuses" on page 1050</a> ".
<b>&lt;Right-click menu&gt;</b>	<ul style="list-style-type: none"> <li>• <b>Filter Vusers.</b> Enables you to filter the Vuser list by Vuser status.</li> <li>• <b>Renumber.</b> Renumbers the list of Vusers in sequential order, starting from 1.</li> <li>• <b>Sort Vusers.</b> Enables you to sort the table by a selected column. To sort the table in ascending/descending order, click the relevant table heading.</li> </ul>

<Vusers table>	Displays the following information about the Vusers: <ul style="list-style-type: none"><li>• <b>ID.</b> The Vuser's ID number</li><li>• <b>Status.</b> The Vuser's status. For details, see "<a href="#">"Vuser Statuses" on page 1050.</a></li><li>• <b>Script.</b> The script run by the Vuser.</li><li>• <b>Virtual Location.</b> The virtual location being emulated (read-only). This column is only visible when Network Virtualization is enabled and set to <b>Per Load Generator</b> mode. For details, see "<a href="#">" Network Virtualization Settings Dialog Box" on page 1155.</a></li><li>• <b>Load Generator.</b> The load generator on which the Vuser is running.</li><li>• <b>Elapsed Time.</b> Amount of time that elapsed in the scenario since the Vuser began running.</li></ul>
----------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Load Generators

### Load Generators - Overview

Load generators are the machines that run the Vuser scripts in your scenarios. Each Vuser script that runs on a load generator results in a single Vuser. Each load generator can run multiple Vuser scripts, thereby resulting in multiple Vusers. While these Vusers run, they create load on your system, enabling you to analyze your system under load.

#### Creating a load generator

To create a load generator, you install LoadRunner's Load Generator software on a host computer. Load generators can be either Windows-based or Linux-based. For details on how to install the appropriate Load Generator software, see the *LoadRunner Installation Guide*.

#### Calculating the number of load generators

To estimate the number of load generators that are needed to run a vuser script, use the **Tools > Load Generator Calculator**.

This feature is a technical preview. The scope of the feature is not final.

If you encounter any unexpected behavior, please contact HP support at [vugen.feedback@hp.com](mailto:vugen.feedback@hp.com) with your feedback. We welcome all comments, suggestions, and feedback in addition to issue reports.

#### Including load generators in a scenario

After you have installed the Load Generator software on a host computer to create a load generator, you can include the new load generator in a scenario. You use the Controller to add the new load generator to a scenario. In order to enable a scenario to develop significant load on a system, a typical scenario may include multiple load generators. You define and maintain the list of load

generators that are available in a scenario. When you add a load generator to the list of load generators in a scenario, you define various attributes of the load generator, such as the platform on which the load generator runs. You can modify some - but not all - of these attributes after the load generator is created.

### Status of a load generator

The Controller's Load Generators dialog box shows the status of each load generator in a scenario. The status of a load generator changes during a scenario run. For example, when you add a load generator to the list of load generators in a scenario, the load generator has the status **Down**. The status of the load generator changes to **Ready** when the load generator is connected to the Controller and is available to run Vuser scripts, and then to **Running** while the load generator executes a Vuser script. For a full list of load generator statuses, see "[Load Generators Dialog Box](#)" on page 1101.

### Load generator configuration

In order to create and run accurate real-life scenarios, you can configure numerous settings for each load generator that is included in a scenario. For details on how to modify these settings, see "[How to Modify Load Generator Settings](#)" on page 1083.

### Local vs. cloud-based load generators

A load generator can be located on either a local computer or in the cloud. A scenario can include both local and cloud-based load generators. The procedure for defining and maintaining load generators is similar for local and cloud-based load generators. For details on cloud-based load generators, see "[Adding a Cloud-Based Load Generator - Overview](#)" on the next page.

### Enabling and disabling a load generator

If a specific load generator is included in the list of load generators for a scenario, but is temporarily unavailable for a particular scenario run, you can disable the load generator instead of removing it permanently from the list. You can then enable the load generator if and when it becomes available.

- For details on how to add a load generator to a scenario, see "[How to Add a Load Generator to a Scenario](#)" on page 1077.
- To set attributes for a specific load generator, see "[Add New Load Generator/Load Generator Information Dialog Box](#)" on page 1085.
- See "[Setting up a Load Generator Environment](#)" on page 1084 for guidelines on how to set up the environment of your load generators.
- To set global settings that apply to all the load generators participating in the scenario, see "[Options Dialog Box](#)" on page 1175.

**Tip:** The LoadRunner standalone Load Generator (LG SA) and standalone Monitor over Firewall (MOFW SA) cannot be installed on the same machine. However, LG SA can be used for monitoring purposes, the same way as the MOFW SA. Note that a single machine cannot be used simultaneously for both running Vusers and monitoring.

## **Adding a Cloud-Based Load Generator - Overview**

This topic discusses adding cloud-based load generators to a scenario. When you add a cloud-based load generator to a scenario, you can add either a new load generator, or a load generator that already exists in a cloud account.

### **Adding a new cloud-based load generator to a scenario**

The process of creating a new load generator in a cloud account is known as *provisioning* the load generator. When you provision a new load generator, the Load Generator software that is required to create the new load generator is installed by the Controller in the cloud. To perform this installation, the Controller uses an "image" of the required load generator. To create the new load generator, you can use either the image that is contained in the default system configuration, or you can specify an alternative image that is included in a custom configuration.


**Note:** You can choose to provision either a single load generator or to simultaneously provision multiple load generators with the same configuration.

### **Adding an existing cloud-based load generator to a scenario**

When you add an existing cloud-based generator to a scenario, you select the account containing existing load generator machines. The Controller then connects to the account and lists all machines associated with that account—not just the load generator machines. You determine which machines are load generators by looking at their images. You then select one or more load generator machines to include in the scenario.

### **Removing a load generator at the end of a scenario run**

You can specify what should happen to load generators at the end of a scenario. The options are to either leave the load generator intact, or to delete the load generator from the cloud. These options apply whether the scenario run ended successfully or failed.



Removal of a load generator at the end of a scenario varies slightly depending on whether the scenario run was successful or failed:

- If the scenario was successful, the load generator is terminated as soon as the scenario ends.

- If the scenario failed, the load generator is terminated at the time specified in the Manage Cloud Accounts dialog box. For details on the cloud account settings, see "[Managing Cloud Accounts - Overview](#)" on page 1079.

### Cloud accounts

Before you can add a cloud-based load generator to a scenario, you must have access to a cloud account. For details on how to make a cloud account available, see "[How to Manage Cloud Accounts](#)" on page 1081.

- For details on how to add either a local load generator or a cloud-based load generator to a scenario, see "[How to Add a Load Generator to a Scenario](#)" below.
- For details about the Load Generator configuration tabs, see "[Add New Load Generator/Load Generator Information Dialog Box](#)" on page 1085.

**Note:** If you intend to run heavy load tests on cloud-based load generators, make sure to notify the cloud vendor before running the tests.

## How to Add a Load Generator to a Scenario

The following steps describe how to add a load generator to a scenario. The procedure varies slightly depending on whether you are adding an on-premises or cloud-based load generator.

### To add load generators to your scenario:

1. In the **Design** tab, click the **Load Generators** button . For details, see "[Load Generators Dialog Box](#)" on page 1101.
2. Add a load generator machine. You can:
  - add an on-premises load generator
  - provision a new cloud-based load generator
  - add a load generator that already exists in a cloud account

### Add an on-premises load generator

1. Click **Add**, and enter the details of the load generator. For details, see "[Add New Load Generator/Load Generator Information Dialog Box](#)" on page 1085.
2. Click **OK**. When you add an on-premises load generator, it remains in the **Down** state until it is connected.

## Provision a new cloud-based load generator

**Note:** The process of creating a new load generator in a cloud account is known as *provisioning* the load generator. You can provision either a single load generator or multiple load generators with the same configuration. You can use either the default system configuration, or define and apply a custom configuration.

1. Click **Add From Cloud > Provision New LG**. The Create New Cloud Load Generator dialog box opens. For details, see "[Create Cloud Load Generator Dialog Box](#)" on page 1088.
2. From the list of available cloud accounts, select the cloud account which will host the new load generator. For details on how to add cloud accounts, see "[How to Manage Cloud Accounts](#)" on page 1081.
3. Specify the number of load generators to provision.
4. Specify whether or not to remove the load generators at the end of the scenario.
5. The first time you provision load generators (optional for the next time you provision load generators, since LoadRunner saves the settings), click **More** to display the **Cloud** and **Connection** tabs. In subsequent provisioning, LoadRunner uses the connection settings that you last applied to a load generator, not necessarily a cloud-based machine.
  - In the **Cloud** tab, select a Region, Instance Type, Image, Security Group, and Key Pair. The default values are the most popular and commonly used settings.
  - In the **Connections** tab, accept the default network profile, or select another one from the drop-down list. Click the  button to open the Network Profile Manager to create a new profile. For details, see "[Network Profile Manager Dialog Box](#)" on page 1104. All of the connection settings will be applied to the new load generators that will be provisioned. For example, if you specify *Port 6080*, the load generator will be created on port 6080 and listen on the same port.
6. Click **Provision** to provision the specified load generators.

## Add an existing cloud-based load generator

1. Click **Add From Cloud > Use Existing LG**. The Use Cloud Load Generator dialog box opens. For details, see "[Use Cloud Load Generator Dialog Box](#)" on page 1090.
2. From the list of cloud accounts, select the cloud account that hosts the existing load generator. For details on how to add cloud accounts, see "[How to Manage Cloud Accounts](#)" on page 1081. A list of available load generators is displayed.
3. Select the load generators that you want to add to the scenario in the **Available Machines** section.
4. Select a **Network Profile** if you defined them beforehand. The network profile indicates the

connection information for the load generator, such as the connection mode, proxy, and ports. To create a new network profile, close this dialog box and choose **Tools > Network Profile Manager**. For details, see "[Network Profile Manager Dialog Box](#)" on page 1104. If the network profile that you chose indicates a different port for an existing load generator (cloud or on-premise), you also need to manually set it on the load generator machine.

5. Click **Add Machine**.

## Managing Cloud Accounts - Overview

Load generators can be hosted on either local computers or in a cloud account. This topic discusses load generators on the cloud. To host a load generator on the cloud, you must have access to a cloud account that will host the load generator. You use the LoadRunner Controller to maintain the list of cloud accounts that are available to host load generators.

**Note:** You must already have access to a cloud account before you can use LoadRunner to use a cloud account for hosting load generators. All costs incurred by the provisioning of cloud machines through LoadRunner, are external to LoadRunner. They are the sole responsibility of the user, and are subject to the cloud vendor's pricing schedule.

When you add a cloud-based load generator to a scenario, you specify which of the available accounts will host the load generator. For details on how to add a cloud account, see "[How to Manage Cloud Accounts](#)" on page 1081. If a cloud account is no longer required by LoadRunner, you can remove the account from the list of available cloud accounts.

**Note:** LoadRunner supports cloud accounts on specified cloud providers only. See the LoadRunner PAM [Product Availability Matrix] for a list of the supported cloud providers.

### Provisioning load generators

On your cloud machines, you use the Controller to create load generators for the cloud account. The process of creating a load generator is known as *provisioning*. When you use the Controller to provision a load generator, the Controller deploys an selected *image* upon the machine with the load generator software. When a load generator is first provisioned, it has the status of "In Progress". When it reaches the "Down" status, it is ready to run Vuser scripts as part of a scenario.

### Terminating load generators at the end of a failed scenario run

You can configure the Controller to remove a load generator from the cloud after the scenario is completed. Load generators are removed in order to reduce cloud usage and the associated costs. For details on how to specify whether or not to remove load generators at the end of a scenario, see "[Adding a Cloud-Based Load Generator - Overview](#)" on page 1076.


If you specify to terminate load generators at the end of a scenario run, its termination differs slightly depending on whether the scenario is completed successfully or fails.

- If the scenario is completed successfully, the load generator is no longer required and is terminated immediately .

- If the scenario fails, then you can specify to terminate the load generator after a specified amount of time after a scenario fails. This delay may be useful because it enables you to access information on the load generator that may indicate why the scenario failed. After the load generator is removed, this information is no longer available.



**Note:** The Controller will terminate a load generator only if the load generator has been configured to be removed at the end of a scenario run. For details on this setting, see "[How to Add a Load Generator to a Scenario](#)" on page 1077.



- For details on how to make a cloud account available to host load generators, see "[How to Manage Cloud Accounts](#)" on the next page.
- For details on the dialog box options, see:
  - "[Manage Cloud Accounts Dialog Box](#)" on the next page
  - "[Create Cloud Load Generator Dialog Box](#)" on page 1088
  - "[Use Cloud Load Generator Dialog Box](#)" on page 1090

## How to Manage Cloud Accounts

To add a cloud account to LoadRunner, and thereby make the account available to host load generators:

1. Open the Controller.
2. Click **Tools > Manage Cloud Accounts**. The Manage Cloud Accounts dialog box opens, and lists all the accounts that are available to host load generators. For details, see "[Manage Cloud Accounts Dialog Box](#)" below.
3. Click the  button.
4. Enter a name for the cloud account. If required, you can modify the name later.
5. Select the provider of the cloud account.

**Note:** LoadRunner supports cloud accounts on specified cloud providers only. See the LoadRunner PAM [product availability matrix] for a list of the supported cloud providers.

6. Specify the provider-specific information for your account. For example, for Amazon EC2, provide the **Access Key ID** and **Secret Access Key** that are required to access the account.  
**Note:** You cannot create multiple accounts using the same provider and the same access key.
7. Specify how long to wait after the end of a failed scenario before removing the load generators from the account. This is useful if the collation did not complete successfully and you need time to determine why it failed.
8. Click **Save**.

**Tip:** To edit the details of a cloud account that appears in the list of accounts that are available to host load generators, click the appropriate  button .

For background information on adding accounts to the list of accounts that can host load generators, see "[Managing Cloud Accounts - Overview](#)" on page 1079.

## Manage Cloud Accounts Dialog Box

This dialog box enables you to manage the cloud accounts that can host load generators. By default, the dialog box displays a list of all those cloud accounts that can host load generators.

<b>To access</b>	<b>Controller &gt; Tools &gt; Manage Cloud Accounts</b>
<b>Important information</b>	The default proxy is used for validating the cloud account.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Manage Cloud Accounts" on the previous page</li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>"Managing Cloud Accounts - Overview" on page 1079</li><li>"How to Add a Load Generator to a Scenario" on page 1077</li><li>"Use Cloud Load Generator Dialog Box" on page 1090</li></ul>

User interface elements are described below:

UI Element	Description
	Adds a cloud account to the list.
	Removes a cloud account from the list.
<b>&lt;Account Name&gt;</b>	The name that you will use to identify the account in the Controller. You can modify the name if and when required.
<b>Username/Password</b>	Placeholder identifiers before an account is selected.
<b>Access Key ID / Secret Access Key</b>	AWS (Amazon Web Service) identifiers that are used to manage IAM (Identity and Access Management) in order to manage users and their security credentials across Amazon's EC2 (Elastic Compute Cloud).  For details, see <a href="http://docs.aws.amazon.com/AWSSecurityCredentials/1.0/AboutAWS Credentials.html#AccessCredentials">http://docs.aws.amazon.com/AWSSecurityCredentials/1.0/AboutAWS Credentials.html#AccessCredentials</a>

<b>Wait xx hours before terminating the LG after a test run whose collation did not succeed.</b>	Lets you specify how long to wait after the post-run collation failed, before terminating the cloud-based load generator. This delay gives you time to access information on the load generator and determine why the collation failed. When a load generator is removed from the cloud, all data saved as part of the load generator is deleted.  You can enter a value from 0 through 168, and specify two digits to the right of the decimal point. For example, a value of 10.50 waits ten and a half hours.
	Edit the details of the cloud account (visible in the expanded details of each cloud account).

## How to Modify Load Generator Settings

The following procedure describes how to modify the settings for a load generator.

1. Open the scenario . The scenario is displayed in the **Design** tab.
2. Click the **Load Generators** button  on the Controller toolbar.
3. Select a load generator, and click **Details**.
4. Modify the details displayed in the configuration tabs at the bottom of the dialog box. For details, see "[Add New Load Generator/Load Generator Information Dialog Box](#)" on page 1085.

## Load Balancing

Load balancing evenly distributes the load generated by Vusers among the requested load generators, ensuring an accurate load test.

When a Windows load generator's CPU usage becomes overloaded, the Controller receives a message and stops loading Vusers on the overloaded load generator, and automatically distributes them among the other load generators taking part in the scenario. Only where there are no other available load generators in the scenario does the Controller stop loading Vusers.

You can monitor the status of a machine's CPU usage using the icons in the Load Generators dialog box (see "[Load Generators Dialog Box](#)" on page 1101). When the CPU usage of a load generator becomes problematic, the icon to the left of the load generator name contains a yellow bar. When the machine becomes overloaded, the icon contains a red bar.

**Note:** Load balancing is available only in manual scenarios in the percentage mode, and in

goal-oriented scenarios.

## Setting up a Load Generator Environment

Follow the guidelines below to set up the environments of your load generators.

- In general, you should always make sure to configure the load generator machine the same as the machine upon which you recorded or prepared the script or test.
- For Java scripts and JUnit tests, verify that the script or test dependencies are available on the load generator machine with the same paths defined in the classpath Run-Time settings. You can do this by mapping network drives, manually copying files, and so forth.
- For NUnit tests, make sure that the NUnit framework is installed on the load generator machine in the same path as the Controller machine.
- For Linux machines, make sure to configure the environment variables as described in "[Linux Environment Variables](#)" on the next page.

## How to Connect/Disconnect a Load Generator

This task describes how to manually connect or disconnect a load generator.

1. On the **Controller** toolbar, click **Load Generators** .
2. Select a load generator in the list and click **Connect/Disconnect**.

## How to Connect to a Linux Load Generator Without Using RSH

This task describes how to connect to a Linux load generator without using RSH.

1. On the Linux load generator, make sure that the agent daemon (m\_agent\_daemon) is running. If not, launch it by running the following command from <load generator installation directory>/bin:

```
m_daemon_setup -install
```

If successful, you will receive the following message:

```
m_agent_daemon <process ID>
```

The agent now keeps running, even if the user is logged off. It only stops running if you run the command explained below, or if you reboot the machine.

**Note:** If you look at the log file **m\_agent\_daemon[xxx].log** in the temp folder, you may see communication errors, even if the installation succeeded. These messages appear because the LoadRunner agent always tries to open Port #443 (because any agent can be an MI Listener, and the MI Listener always listens to this port), and in Linux machines, this port cannot be opened by any user except for the root user. However, this does not interfere with using this agent for the load generator.

2. In the Controller, in the **Load Generator Information** dialog box > **Linux Environment** tab, select the **Don't use RSH** option. Connect as usual.

For details, see "[Load Generator Configuration > Linux Environment Tab](#)" on page 1096.

### **To stop the agent daemon:**

Run the following command from the **<LR\_root>/bin** folder:

```
m_daemon_setup -remove
```

This stops the m\_agent\_daemon. If successful, you receive the following message:

```
m_agent_daemon is down.
```

## **Linux Environment Variables**

To work with a load generator in a Linux environment, your Linux startup configuration file needs to include specific environment variables. To set the environment variables, users need to add the **env.csh** script to their startup configuration file.

Linux Users	Startup Configuration File
C shell	.cshrc
Bourne and Korn shell	.profile

Add the following line in the startup configuration file:

```
source <load generator installation directory>/env.csh
```

For example:

```
source /opt/HP/HP_LoadGenerator/env.csh
```

## **Add New Load Generator/Load Generator Information Dialog Box**

The Add New Load Generator dialog box enables you to add a new local load generator to the scenario. The Load Generator Information dialog box enables you to view and edit information about the selected load generator.

<b>To access</b>	Controller toolbar >  .
	<ul style="list-style-type: none"> <li><b>Add New Load Generator dialog box:</b> Click <b>Add</b>.</li> <li><b>Load Generator Information dialog box:</b> Select a load generator and click <b>Details</b>.</li> </ul>
<b>Important information</b>	After adding a load generator, it appears in the Load Generators list with a <b>Down</b> status.
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>"How to Add a Load Generator to a Scenario" on page 1077</li> <li>"How to Modify Load Generator Settings" on page 1083</li> </ul>
<b>See also</b>	<a href="#">"Load Generators - Overview" on page 1074</a>

User interface elements are described below:

UI Element	Description
	<b>More/Less.</b> Shows/hides the tabs where you configure the load generator's details. For details, see below.
(Add New Load Generator dialog box only)	
<b>Enable load generator to take part in the scenario</b>	When selected, enables the load generator to participate in the scenario. When cleared, the load generator is disabled, and therefore does not participate in the scenario. This is useful in the following cases: <ul style="list-style-type: none"> <li>If a load generator is unavailable for a particular scenario run, you can exclude it temporarily instead of removing it entirely from the list of load generators that are available for the scenario.</li> <li>You can disable load generators to isolate a specific machine to test its performance.</li> </ul>
<b>Name</b>	The name of the load generator.
<b>Platform</b>	The platform on which the load generator is installed, either Windows or Linux.
<b>Temporary directory</b>	The location, on the load generator, where the Controller can store temporary files. <b>Default:</b> If left empty, during a scenario run LoadRunner stores the temporary files on the load generator in a temporary folder specified by the load generator's TEMP or TMP environment variables.

## Load Generator Configuration Tabs

User interface elements are described below:

UI Element	Description
<b>Connection Log tab</b> (Load Generator Information dialog box only)	<p>Displays the standard output and standard errors generated as the Controller connects to the selected Linux load generator. You can change the command that the Controller sends to the remote bridge in order to connect to the load generator. See "<a href="#">Load Generator Configuration &gt; Connection Log Tab</a>" on page <a href="#">1091</a>.</p> <p><b>Note:</b> Available in Expert mode only.</p>
<b>Run-Time File Storage tab</b>	<p>Enables you to specify the result folder for the performance data that LoadRunner gathers from each load generator during a scenario. See "<a href="#">Load Generator Configuration &gt; Run-Time File Storage Tab</a>" on page <a href="#">1092</a>.</p>
<b>Run-Time Quota tab</b>	<p>Enables you to specify the maximum number of Vusers that the load generator can initialize or stop simultaneously. See "<a href="#">Load Generator Configuration &gt; Run-Time Quota Tab</a>" on page <a href="#">1093</a>.</p>
<b>Connections tab</b>	<p>Enables you to manage network profiles and run Vusers over a firewall. See "<a href="#">Load Generator Configuration &gt; Connections Tab</a>" on page <a href="#">1093</a>.</p>
<b>Status tab</b>	<p>Displays details about the status of the load generator. See "<a href="#">Load Generator Configuration &gt; Status Tab</a>" on page <a href="#">1094</a>.</p>
<b>Terminal Services tab</b>	<p>The Terminal Services Manager which enables you to distribute Vusers running in your load testing scenario on terminal servers. See "<a href="#">Load Generator Configuration &gt; Terminal Services Tab</a>" on page <a href="#">1094</a>.</p>
<b>Linux Environment tab</b>	<p>Enables you to configure the login parameters and shell type for each Linux load generator. See "<a href="#">Load Generator Configuration &gt; Linux Environment Tab</a>" on page <a href="#">1096</a>.</p>
<b>Vuser Limits tab</b> (Add New Load Generator dialog box only)	<p>Enables you to modify the maximum number of GUI, RTE, and other Vusers that the load generator can run. See "<a href="#">Load Generator Configuration &gt; Vuser Limits Tab</a>" on page <a href="#">1098</a>.</p>
<b>Vuser Status tab</b> (Load Generator Information dialog box only)	<p>Displays the status of all the Vusers connected to the load generator. See "<a href="#">Load Generator Configuration &gt; Vuser Status Tab</a>" on page <a href="#">1099</a>.</p>
<b>Network Virtualization tab</b>	<p>Allows you to apply network virtualization to your scenario. See "<a href="#">Load Generator Configuration &gt; Network Virtualization Tab</a>" on page <a href="#">1100</a>.</p>

## Create Cloud Load Generator Dialog Box

The Create Cloud Load Generator dialog box enables you to deploy a new cloud-based load generator.

<b>To access</b>	<ol style="list-style-type: none"><li>Click  on the Controller toolbar to open the <b>Load Generator dialog box</b>.</li><li>Click <b>Add from Cloud</b>.</li><li>Click <b>Provision New LG</b>.</li></ol>
<b>Relevant tasks</b>	<a href="#">"How to Manage Cloud Accounts" on page 1081</a>
<b>See also</b>	<ul style="list-style-type: none"><li><a href="#">"Managing Cloud Accounts - Overview" on page 1079</a></li><li><a href="#">"Use Cloud Load Generator Dialog Box" on page 1090</a></li></ul>

User interface elements are described below:

UI Element	Description
<b>Provision</b>	Provision the load generator(s) for the scenario according to the last configuration used for the selected account. This button is only enabled after you select a cloud account. If this is the first time you are provisioning load generators, the default configuration is used.
<b>&lt;number of load generators&gt;</b>	The number of cloud-based load generators to provision.
<b>Terminate the Load Generator when load test is finished</b>	Terminates the current deployment when the load test is complete.
	<b>More/Less.</b> Shows/hides the tabs where you configure the cloud load generator parameters and the network profile to be used by the load generator. LoadRunner saves your selections for future provisioning. For details, see below.

## Create Cloud Load Generator Tabs

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Cloud tab</b>	<p>The Cloud Machine parameters. You can configure the following parameters:</p> <ul style="list-style-type: none"><li>• <b>Region.</b> The region (geographic location) and the availability-zone (isolated location within the region). For example <b>us-west-1</b>.</li><li>• <b>Instance Type.</b> The hardware configuration of the host computer that will be provisioned. This will impact parameters such as storage and memory. For example, <b>m1.xlarge</b>.</li><li>• <b>Image.</b> A template that contains a software configuration for your server such as the operating system. In the case of LoadRunner, the image will also contain the load generator software. For information on creating custom cloud images, see below.</li><li>• <b>Security Group.</b> The security group is a firewall-like mechanism that controls traffic to or from its associated instances. If you omit this property, the cloud provider's default security group is used. The default security group does not allow the Controller to connect to load generators using its default port. Therefore, you must create your own security group and enable it for all of the relevant communication ports. This includes the LoadRunner port, default port (54345), and any port set by the communication channel infrastructure. (See "<a href="#">Network and Security Manager</a>" on page 1105) In addition, if you are going to access your load generators manually, you need to enable the security group for RDP access.</li><li>• <b>Key Pair.</b> (optional - only if you want to connect remotely) The key pair encrypts and decrypts your login information.</li></ul> <p>Refer to your cloud provider's website for further information about these parameters.</p>
<b>Connections tab</b>	<p>Shows the details of the network profile assigned to the load generator, such as the proxy information, connection mode, and ports.</p> <ul style="list-style-type: none"><li>• To use a network profile other than the default, select one from the drop-down list.</li><li>• To create a new profile, click the  button to open the Network Profile Manager. For details, see "<a href="#">Network Profile Manager Dialog Box</a>" on page 1104.</li></ul>

### Creating a Custom Image

By default, LoadRunner provides several built-in images. To create a custom image:

1. Start a new machine in the cloud. We recommend that you use an existing image as a basis for the new one.
2. Install a Load Generator on the cloud machine. The setup file is in the DVD's **Standalone Applications** folder.

3. Install any additional software required, for example, a Citrix client.
4. if you are going to use the Citrix protocol, check that your network can access the cloud machine. We recommend that you disable firewalls completely on the cloud machine, and use the network management, such as security groups, provided by the cloud provider.
5. Register the **LGCloudAgent** service on the machine using the following command:  

```
sc create LGCloudAgent binPath= "c:\Program Files (x86)\HP\Load
Generator\bin\LGCloudAgent.exe" start= auto
```
6. Convert the cloud machine to the image, following the instructions provided by the cloud provider.
7. Mark your new image as a load generator, to allow it to be recognized by the Controller. Set the description to "HP LR LG, PC Compatible"
8. Copy the image to all required regions.

## Use Cloud Load Generator Dialog Box

The Use Cloud Load Generator dialog box enables you to add an existing cloud-based load generator to your scenario.

<b>To access</b>	<ol style="list-style-type: none"><li>1. Click  on the Controller toolbar to open the <b>Load Generator dialog box</b>.</li><li>2. Click <b>Add from Cloud</b>.</li><li>3. Click <b>Use Existing LG</b>.</li></ol>
<b>Relevant tasks</b>	<a href="#">"How to Manage Cloud Accounts" on page 1081</a>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Managing Cloud Accounts - Overview" on page 1079</a></li><li>• <a href="#">"Adding a Cloud-Based Load Generator - Overview" on page 1076</a></li><li>• <a href="#">"Create Cloud Load Generator Dialog Box" on page 1088</a></li></ul>

User interface elements are described below:

UI Element	Description
<b>Account</b>	A drop-down list of your cloud accounts.

<b>Available Machines</b>	A list of cloud-based machines available for the current account. The grid contains the following columns: <b>Name</b> , <b>Region/Availability Zone</b> , <b>Launch Time</b> , and <b>Image</b> . Click a column name to sort it by that criteria. To show only machines with images that can be used as load generators, expand the <b>Image</b> drop-down, and clear the relevant check box.
<b>Network Profile</b>	A drop-down list of the network profiles that were defined for the active scenario. This allows you to configure the network settings only once for all machines included in the scenario. For details, see " <a href="#">"Network Profile Manager Dialog Box" on page 1104</a> ".
<b>Add (x) Machine(s)</b>	Adds the selected load generators to the list in the Load Generators dialog box.

## Load Generator Configuration > Connection Log Tab

This tab displays the standard output and standard errors generated as the Controller connects to the selected Linux load generator and enables you change the command that the Controller sends to the remote bridge in order to connect to the load generator.

<b>To access</b>	<b>Controller</b> toolbar >  > Details
<b>Important information</b>	This tab is displayed only when the Controller is in Expert mode.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">"How to Add a Load Generator to a Scenario" on page 1077</a></li><li>• <a href="#">"How to Modify Load Generator Settings" on page 1083</a></li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Load Generators - Overview" on page 1074</a></li><li>• <a href="#">"Expert Mode" on page 1170</a></li></ul>

User interface elements are described below:

UI Element	Description
<b>Bridge cmd</b>	The command sent by the Controller to the remote bridge in order to connect the Linux load generator. <b>Note:</b> This command replaces the default bridge command sent by the Controller.
<b>Rsh standard errors</b>	Displays rsh standard errors as the Controller connects to the selected Linux load generator.
<b>Rsh standard output</b>	Displays rsh standard output as the Controller connects to the selected Linux load generator.

## Load Generator Configuration > Run-Time File Storage Tab

This tab enables you to specify the results folder for the performance data that LoadRunner gathers from this load generator during a scenario run.

To access	Controller toolbar >  > Add or Details
Important information	<ul style="list-style-type: none"><li>The folder specified here stores the result files gathered on the selected load generator.</li></ul> <p>A global results folder for all load generators is specified in the <b>Tools &gt; Options</b> dialog box. For details, see "<a href="#">Options &gt; Run-Time File Storage Tab</a>" on page <a href="#">1182</a>.</p> <p><b>Note:</b> If the settings specified here differ to the global load generator settings, the settings specified here take preference for this particular load generator.</p> <ul style="list-style-type: none"><li>If the load generator is <b>localhost</b>, then LoadRunner stores the scripts and results on a shared network drive, and the options on this tab are all disabled.</li><li>If you are monitoring over a firewall, the settings in this tab are not relevant.</li></ul>
Relevant tasks	<ul style="list-style-type: none"><li><a href="#">"How to Add a Load Generator to a Scenario" on page 1077</a></li><li><a href="#">"How to Modify Load Generator Settings" on page 1083</a></li></ul>
See also	<ul style="list-style-type: none"><li><a href="#">"Run-Time File Storage Locations" on page 1170</a></li><li><a href="#">"Options &gt; Run-Time File Storage Tab" on page 1182</a></li></ul>

User interface elements are described below:

UI Element	Description
Scripts and results stored	Select where to store the results of the scenario run and/or Vuser scripts gathered from the selected load generator during a scenario run: <ul style="list-style-type: none"><li><b>As defined in Tools &gt; Options &gt; Run-Time File Storage.</b> Stores the results as specified in the global settings.</li><li><b>In temporary directory on &lt;load generator name&gt;.</b> Instructs the Controller to save the run-time files on a hard drive of the load generator machine.</li><li><b>On a shared network drive.</b> Instructs the Controller to save the scenario results and/or the Vuser scripts on a shared network drive. A shared network drive is a drive to which the Controller and all the load generators in the scenario have read and write permissions.</li></ul>

## Load Generator Configuration > Run-Time Quota Tab

This tab enables you to specify a maximum number of Vuser types that the load generator should initialize or stop simultaneously, so as to reduce load on the load generator.

To access	Controller toolbar >  > Add or Details
Important Information	<p>The settings specified here are relevant for the selected load generator. You can set run-time quotas for all load generators in a scenario from the <b>Tools &gt; Options &gt; Run-Time Settings</b> tab. For details on setting global run-time quotas, see "<a href="#">"Options &gt; Run-Time Settings Tab" on page 1182</a>.</p> <p><b>Note:</b> If the settings specified here differ to the global load generator settings, the settings specified here take preference for this particular load generator.</p>
Relevant tasks	<ul style="list-style-type: none"><li><a href="#">"How to Add a Load Generator to a Scenario" on page 1077</a></li><li><a href="#">"How to Modify Load Generator Settings" on page 1083</a></li></ul>
See also	<ul style="list-style-type: none"><li><a href="#">"Options &gt; Run-Time Settings Tab" on page 1182</a></li></ul>

User interface elements are described below:

UI Element	Description
	Resets values to their defaults.
Vuser Quota	<ul style="list-style-type: none"><li><b>Number of Vusers that may be initialized at one time - &lt;current load generator&gt;</b>. The maximum number of Vusers that the current load generator can initialize simultaneously. <b>Default:</b> 50 <b>Maximum value:</b> 999</li><li><b>Limit the number of users that may be stopped at one time to</b>. The maximum number of Vusers that the current load generator can stop simultaneously. <b>Default:</b> 50</li></ul>

## Load Generator Configuration > Connections Tab

This tab enables monitoring or running Vusers over a firewall. It also allows you to select a connection profile, for customizing the ports used by the load generator and MI listener.

To access	Controller toolbar >  > Add or Details
-----------	---------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	<ul style="list-style-type: none"><li>If the load generator is connected, you cannot change values in this tab. To disconnect a load generator, select it in the Load Generators dialog box and click <b>Disconnect</b>. The load generator status changes to <b>Down</b>, and you can change the settings.</li><li>If the load generator is <b>localhost</b>, this tab is disabled.</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Add a Load Generator to a Scenario" on page 1077</li><li>"How to Modify Load Generator Settings" on page 1083</li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>"Network Profile Manager Dialog Box" on page 1104</li></ul>

User interface elements are described below:

UI Element	Description
<b>Choose Network Profile</b>	A drop-down list of network profiles defining the connection properties of the load generator. Each profile defines whether to connect directly or via an MI Listener. You can also provide information to connect to the load generator via a proxy.
<b>Manage Profiles</b>	Opens the Network Profile Manager. For details, see "Network Profile Manager Dialog Box" on page 1104.

## Load Generator Configuration > Status Tab

This tab displays details about the status of the load generator.

<b>To access</b>	Controller toolbar >  > Details
<b>Relevant tasks</b>	"How to Modify Load Generator Settings" on page 1083

User interface elements are described below:

UI Element	Description
<b>Details</b>	Error and other run-time information about the selected load generator.
<b>Load Generator Status</b>	The status of the load generator.

## Load Generator Configuration > Terminal Services Tab

This tab displays the Terminal Services Manager which enables you to distribute Vusers running in your load testing scenario on terminal servers.

<b>To access</b>	Controller toolbar >  > Add or Details
------------------	---------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	This feature is not supported if the load generator is located over a firewall.
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>"<a href="#">How to Add a Load Generator to a Scenario</a>" on page 1077</li> <li>"<a href="#">How to Modify Load Generator Settings</a>" on page 1083</li> </ul>
<b>See also</b>	<a href="#">"Terminal Services Overview" on page 1146</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Defaults</b>	Resets values to their defaults.
<b>&lt;Connection Options&gt;</b>	<ul style="list-style-type: none"> <li><b>Connect to existing Terminal Services Sessions.</b> Enables connection to existing (open) terminal sessions.   <b>Note:</b> If you select this option, you must open a terminal client session manually for each terminal that you want to run Vusers on during the scenario.</li> <li><b>Create new Terminal Services Sessions.</b> Enables the Controller to open and close terminal sessions automatically using a <b>user name</b>, <b>password</b>, and <b>domain</b> for the Terminal Services session.</li> <li><b>Show Terminal Services clients on the Controller machine.</b> Enables interaction with new Terminal Services sessions using the RDP client.</li> </ul>
<b>Enable Terminal Services Manager</b>	<p>Enables the Controller to manage load automatically using terminal sessions on the load generator.</p> <p><b>Note:</b> When enabled, you can see the load generator's name only, without adding any extra references.</p> <p><b>Example:</b> If you need to use three load generator sessions, <b>my_machine</b>, <b>my_machine:1</b>, and <b>my_machine:2</b>, then in the load generator list, you need only insert the load generator, <b>my_machine</b>, and enable the Terminal Services Manager for three terminals (<b>Number of terminals = 3</b> - see below). If not enabled, you need to insert each of the three terminals as separate load generators: <b>my_machine</b>, <b>my_machine:1</b>, and <b>my_machine:2</b>.</p>
<b>Maximum number of Vusers per terminal</b>	The maximum number of Vusers that you want to run in a terminal session. This depends on the Vuser type used in the script. <b>Default:</b> 50 <b>Example:</b> For GUI Vusers, the maximum is <b>one</b> Vuser for each terminal session.
<b>Number of terminals</b>	The number of terminals you want to use in your scenario. You must open a terminal client session for each terminal on which you want to run Vusers during the scenario. <b>Default:</b> 2

## **Load Generator Configuration > Linux Environment Tab**

This tab enables you to configure the login parameters and shell type for each Linux load generator.

<b>To access</b>	<b>Controller toolbar &gt;</b>  <b>&gt; Add or Details</b>
<b>Important information</b>	<ul style="list-style-type: none"><li>• This tab is not available for a load generator running Vusers or monitoring over a firewall.</li><li>• Editable only when the load generator is on a Linux platform.</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• "<a href="#">How to Add a Load Generator to a Scenario</a>" on page 1077</li><li>• "<a href="#">How to Modify Load Generator Settings</a>" on page 1083</li><li>• "<a href="#">How to Connect to a Linux Load Generator Without Using RSH</a>" on page 1084</li></ul>

User interface elements are described below:

UI Element	Description
<b>Login as</b>	<p>The user's credentials for logging in to the Linux environment:</p> <ul style="list-style-type: none"><li>• <b>Name.</b> If the load generator is Linux-based, set the login information for the load generator.</li></ul> <p><b>Default:</b> LoadRunner uses your Windows user name for the Linux login. That is, if your Windows login is <b>Irunner</b>, the Controller logs in to the load generator as Irunner. To log in to a Linux-based load generator using a different login name, select <b>Name</b> and specify the desired Linux login name.</p> <p>Using this option, you can log in to the Windows Controller as <b>bill</b> and connect to the Linux load generator as <b>mike</b>. However, you should make sure that mike allows bill to log in using his name. This can be done by adding the line "<b>+ bill</b>" at the beginning of mike's .rhosts file.</p> <ul style="list-style-type: none"><li>• <b>Use lower case for login names.</b> Instructs LoadRunner to use lower case names during login to avoid case-sensitive issues with the Linux operation system.</li></ul> <p><b>Local User.</b> (Expert mode only) Linux load generators that use the rsh shell to establish a connection as the current Windows user (due to security considerations). To "mislead" rsh and log in as a user other than the current Windows login, select <b>Local user</b> and specify the desired Linux login name. Because modifying the local user name is a security breach for rsh, this option should be used only when you encounter a problem connecting to the remote machine.</p>


UI Element	Description
<b>Shell Settings</b>	<p>The Linux shell settings for the remote Linux load generator.</p> <p><b>Default:</b> The Controller connects remotely to the Linux load generator without using rsh (remote shell).</p> <ul style="list-style-type: none"> <li>• <b>Don't use RSH.</b> Connects to the remote load generator without using RSH. In this case, you need to activate the agent daemon on the load generator manually.</li> </ul> <p><b>Note:</b> If you do want to connect using RSH, clear this check box, make sure that RSH is enabled on the load generator, and make sure that the agent daemon is not already running on the load generator. If the agent daemon is running, stop it by running the following command from the &lt;LR_root&gt;/bin folder: m_daemon_setup -remove</p> <ul style="list-style-type: none"> <li>• <b>Default shell.</b> The default shell on the Linux load generator: <b>csh</b> (C Shell—the default), <b>bsh</b> (Bourne Shell), or <b>ksh</b> (Korn Shell).</li> </ul> <p>To work with the load generator, your Linux startup configuration file needs to include specific environment variables. For details, see "<a href="#">Linux Environment Variables</a>" on page 1085.</p> <ul style="list-style-type: none"> <li>• <b>Initialization command.</b> Command line options for LoadRunner to use when logging in to a Linux system. This initialization command runs as soon as the shell opens.</li> </ul> <p><b>Example:</b> You could select <b>ksh</b> and use the following initialization command:  <pre>source .profile;</pre></p>

## Load Generator Configuration > Vuser Limits Tab

This tab enables you to modify the maximum number of GUI, RTE, and other Vusers that the load generator can run.

<b>To access</b>	Controller toolbar >  > Add or Details
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>• "<a href="#">How to Add a Load Generator to a Scenario</a>" on page 1077</li> <li>• "<a href="#">How to Modify Load Generator Settings</a>" on page 1083</li> </ul>

User interface elements are described below:

UI Element	Description
	Resets values to their defaults.

<b>Available Types</b>	The types of Vusers the load generator should run. The types of Vusers are: <ul style="list-style-type: none"><li>• <b>GUI</b></li><li>• <b>RTE</b></li><li>• <b>Other Vusers</b></li></ul>
<b>Maximum Active</b>	The maximum number of each type of Vuser that the load generator should run. <b>Defaults:</b> <ul style="list-style-type: none"><li>• GUI: 1</li><li>• RTE: 1000</li><li>• Other Vusers: 5000</li></ul> <b>Note:</b> The maximum number of active Vusers that you specify must not exceed the number of Vusers that you are licensed to run. To check your Vuser licensing limitations, open the LoadRunner License Utility by selecting <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; License &gt; LoadRunner License Utility</b> .

## Load Generator Configuration > Vuser Status Tab

This tab enables you to view the status of all the Vusers connected to the load generator.

<b>To access</b>	Controller toolbar >  > Add or Details
<b>Important information</b>	This tab is visible only when the load generator is connected.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">"How to Add a Load Generator to a Scenario" on page 1077</a></li><li>• <a href="#">"How to Modify Load Generator Settings" on page 1083</a></li></ul>
<b>See also</b>	<a href="#">"Configuring Network Virtualization Settings" on page 1149</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description

<Vuser Status>	The status of the Vusers: <ul style="list-style-type: none"><li><b>Pending.</b> Vusers are waiting to initialize.</li><li><b>Initializing.</b> Vusers are in the initialization state.</li><li><b>Active.</b> Vusers are actively running in the scenario.</li></ul>
GUI	The number of GUI Vusers that are in the <b>Pending</b> , <b>Initializing</b> , and <b>Active</b> states.
Other Vusers	The number of Vusers—other than GUI and RTE Vusers—that are in the <b>Pending</b> , <b>Initializing</b> , and <b>Active</b> states.
RTE	The number of RTE Vusers that are in the <b>Pending</b> , <b>Initializing</b> , and <b>Active</b> states.
Totals	The total number of Vusers that are in the <b>Pending</b> , <b>Initializing</b> , and <b>Active</b> states.

## Load Generator Configuration > Network Virtualization Tab

This tab shows the network virtualization location for your scenario.

To access	Controller toolbar >  > Add or Details
Important information	<ul style="list-style-type: none"><li>To enable network virtualization, see "<a href="#">Network Virtualization Settings Dialog Box</a>" on page 1155.</li></ul>
Relevant tasks	<ul style="list-style-type: none"><li><a href="#">"How to Run a Scenario with Network Virtualization"</a> on page 1152</li><li><a href="#">"How to Add a Load Generator to a Scenario"</a> on page 1077</li><li><a href="#">"How to Modify Load Generator Settings"</a> on page 1083</li></ul>
See also	<a href="#">"Configuring Network Virtualization Settings"</a> on page 1149

User interface elements are described below:

UI Element	Description
Network Virtualization Settings button	Opens the " <a href="#">Network Virtualization Settings Dialog Box</a> " on page 1155. This dialog box lets you enable Network Virtualization, or change the working mode ( <b>Per Group</b> or <b>Per Load Generator</b> ). It also provides a link to the Shunra screens, allowing you to configure the virtualization properties.

<b>Virtual Location</b>	The name of the virtual location to emulate. For details, see " <a href="#">Virtual Locations Overview</a> " on page 1151. (only visible when Network Virtualization is enabled and <b>Per Load Generator</b> mode selected.)
<b>Description</b>	The description of the virtual location as entered in the " <a href="#">Network Virtualization Settings Dialog Box</a> " on page 1155

## Load Generators Dialog Box

This dialog box enables you to manage the load generators defined for the scenario.

<b>To access</b>	<ul style="list-style-type: none"><li>Open a scenario and click  on the Controller toolbar</li><li>Select <b>Scenario &gt; Load Generators</b></li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"<a href="#">How to Add a Load Generator to a Scenario</a>" on page 1077</li><li>"<a href="#">How to Modify Load Generator Settings</a>" on page 1083</li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>"<a href="#">Load Generators - Overview</a>" on page 1074</li><li>"<a href="#">Manage Cloud Accounts Dialog Box</a>" on page 1081</li></ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Connect / Disconnect</b>	<ul style="list-style-type: none"><li><b>Connect.</b> Instructs the Controller to connect the selected load generator. When connected, the status of the load generator changes from <b>Down</b> to <b>Ready</b>.</li><li><b>Disconnect.</b> When the load generator is connected, the button automatically changes to <b>Disconnect</b>. When clicked, the status of the load generator changes to <b>Down</b>.</li></ul>
<b>Add</b>	Opens the Add New Load Generator dialog box where you specify and add a new local load generator for the scenario. See " <a href="#">Add New Load Generator/Load Generator Information Dialog Box</a> " on page 1085. <b>Note:</b> When you add a local load generator, the status of the load generator is set to <b>Down</b> until it is connected.
<b>Add From Cloud</b>	Enables you to add a cloud-based load generator to the scenario. The load generator can be either a new load generator or a load generator that already exists in the cloud. <b>Note:</b> When you add a local load generator, the status of the load generator is set to <b>Down</b> until it is connected.

<b>Delete</b>	Removes the load generator from the list of load generators that are available to run Vuser scripts during the scenario.  <b>Note:</b> If the selected load generator is cloud-based, you can select to delete the load generator from the cloud account as well.  A load generator can be removed only when it is disconnected.
<b>Reset</b>	Attempts to reset a failed load generator to the <b>Down</b> status.
<b>Details</b>	Opens the Load Generator Information dialog box where you can view and modify information about the selected load generator. See " <a href="#">Add New Load Generator/Load Generator Information Dialog Box</a> " on page 1085.
<b>Disable/Enable</b>	Instructs the Controller to disable or enable the selected load generator. When a load generator is disabled, the details of the load generator are displayed in gray.
<b>&lt;icons&gt;</b>	Display the status of the load generator's CPU usage:  The load generator is available to run additional Vuser scripts.  There is a problem with the CPU usage of the load generator.  The load generator is overloaded.  The status of the load generator is unknown. This applies when the specified load generator name or IP address cannot be resolved.  The Controller monitors the CPU usage of each load generator, and stops loading Vusers on a load generator when the load generator is overloaded. These icons are displayed for Windows-based load generators only.

<Load Generator table>	<p>Displays the following information:</p> <ul style="list-style-type: none"><li>• <b>Name.</b> The name or IP address of the load generator.] <b>Note:</b> For cloud-based load generator machines, you can freely modify the name of the load generator and it will not affect the IP address that was provisioned for the machine. For physical load generators, however, this name is the DNS name, and should not be modified.</li><li>• <b>Status.</b> The current status of the load generator</li></ul> <table border="1"><tbody><tr><td><b>Ready</b></td><td>The load generator is connected, and is ready to run Vuser scripts. If the connection is secure, an icon  indicates a secure connection.</td></tr><tr><td><b>Connecting</b></td><td>The Controller is in the process of connecting to the load generator.</td></tr><tr><td><b>Active</b></td><td>The load generator is running Vusers. If the connection is secure, an icon  indicates a secure connection.</td></tr><tr><td><b>Down</b></td><td>The load generator is not connected.</td></tr><tr><td><b>Failed</b></td><td>A connection with the load generator could not be established.</td></tr><tr><td><b>In Progress</b></td><td>The load generator is being provisioned. This status only applies to cloud-based load generators.</td></tr></tbody></table> <ul style="list-style-type: none"><li>• <b>Platform.</b> The type of platform on which the load generator is running. The platform indicates whether the load generator is Windows-based, Linux-based, or cloud-based. <b>Note:</b> The LoadRunner version of the load generator must match the version of the Controller. You can determine the version of the load generator from the Image string. To determine the version of the Controller, select <b>Help &gt; About</b>.</li><li>• <b>Type.</b> Indicates whether the load generator is local or cloud-based. For cloud-based load generators, <b>Type</b> displays the name of the cloud provider.</li><li>• <b>Virtual Location.</b> The virtual location to emulate (only visible when Network Virtualization is enabled and set to <b>Per Load Generator</b> mode). Click the cell to select a location from the drop-down list. To clear the value, select the first entry of the drop-down, an empty field.</li><li>• <b>Details.</b> If the connection between the Controller and the load generator fails, displays details about why the connection failed.</li></ul>	<b>Ready</b>	The load generator is connected, and is ready to run Vuser scripts. If the connection is secure, an icon  indicates a secure connection.	<b>Connecting</b>	The Controller is in the process of connecting to the load generator.	<b>Active</b>	The load generator is running Vusers. If the connection is secure, an icon  indicates a secure connection.	<b>Down</b>	The load generator is not connected.	<b>Failed</b>	A connection with the load generator could not be established.	<b>In Progress</b>	The load generator is being provisioned. This status only applies to cloud-based load generators.
<b>Ready</b>	The load generator is connected, and is ready to run Vuser scripts. If the connection is secure, an icon  indicates a secure connection.												
<b>Connecting</b>	The Controller is in the process of connecting to the load generator.												
<b>Active</b>	The load generator is running Vusers. If the connection is secure, an icon  indicates a secure connection.												
<b>Down</b>	The load generator is not connected.												
<b>Failed</b>	A connection with the load generator could not be established.												
<b>In Progress</b>	The load generator is being provisioned. This status only applies to cloud-based load generators.												

<b>&lt;Right-click menu&gt;</b>	<ul style="list-style-type: none"><li>• <b>Save List As Default.</b> Saves the current list of load generators as the default list.</li><li>• <b>Load Default List.</b> Loads the default list of load generators.</li><li>• <b>Filter Hosts.</b> Enables you to filter the load generator list by status: <b>Active</b>, <b>Ready</b>, <b>Down</b>, or <b>Failed</b>.</li><li>• <b>Sort Hosts.</b> Enables you to sort the Load Generator table by name, status, or type. To sort the table in ascending/descending order, click the relevant table heading.</li></ul>
---------------------------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## **Network Profile Manager Dialog Box**

This dialog box enables you to set up network profiles for your load generator. For each profile, you can allow communication over a firewall. You can also customize the ports used by the load generator and MI listener.

<b>To access</b>	<p>Do one of the following:</p> <ul style="list-style-type: none"><li>• <b>Load Generator dialog boxes</b><ol style="list-style-type: none"><li>a. Controller toolbar &gt; Load Generators .</li><li>b. In the Load Generators dialog box, click <b>Add</b> or <b>Details</b>.</li><li>c. Select the <b>Connections</b> tab.</li><li>d. Click <b>Network Profile Manager</b>.</li></ol></li><li>• <b>Tools &gt; Network Profile Manager</b></li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>If the load generator is connected, you cannot change values in its profile. To disconnect a load generator, select the load generator click <b>Disconnect</b>. The load generator status changes to <b>Down</b>, and you can change the settings.</li><li>Network Profile names may only have English characters.</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Add a Load Generator to a Scenario" on page 1077</li><li>"How to Modify Load Generator Settings" on page 1083</li></ul>

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Profiles Toolbar</b>	Allows you to manage the profiles in the list.  Add a new profile.  Delete the selected profile.  Clone the selected profile.  Set the selected profile as default.  Import a previously saved profile.  Export the selected profile to a file for future use.
<b>Network Profile Name</b>	A list of all of the defined profiles.
<b>Proxy Settings &gt; Use proxy</b>	Allows you to access a load generator through a proxy server. <b>Obtain the proxy setting from default browser.</b> Uses your default browser proxy definitions. <b>Use custom proxy server.</b> Specifies the URL, port, and credentials for the proxy server.  <b>Note:</b> LoadRunner currently supports basic and NTLM proxy authentication.
<b>Connection Mode</b>	Indicates how to connect to the LoadRunner agent. <b>Connect directly to Load Generator Agent</b> (default). Connects to the load generator directly via the specified <b>Port</b> . The default port is 54345. <b>Connect via MI Listener.</b> Connects to the load generator through the MI Listener. This is useful when the load generator is behind a firewall. You specify the <b>Name</b> and <b>Port</b> of the MI Listener that the load generator uses to communicate over the firewall. The default port is 50500.
<b>Enable SSL</b>	Enables a secure connection between the Controller and load generator. This is enabled automatically when using a proxy.

## Network and Security Manager

This feature is a technical preview. The scope of the feature is not final.

If you encounter any unexpected behavior, please contact HP support at [vugen.feedback@hp.com](mailto:vugen.feedback@hp.com) with your feedback. We welcome all comments, suggestions, and feedback in addition to issue reports.

LoadRunner's Network and Security Manager lets you configure the settings on local and remote machines from a single location. It allows you to update the following agent-related settings:

- Agent ports
- Agent settings
- Authentication settings

If you want to automate your test and run it through the command line, use the **lr\_agent\_settings.exe**, tool described in "[Network and Security Manager - Command Line Tool](#)" on page [1108](#).

<b>To access</b>	<b>Start Menu ... &gt; HP LoadRunner &gt; Tools &gt; Network and Security Manager</b>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• "How to Change a Certificate" on page 1338</li><li>• "How to Create and Use Digital Certificates" on page 1346</li></ul>

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>New Host</b>	Creates an entry for a new host in the host list. If you already have at least one host defined, the values for the new host will be taken from the host that you select in the list.
<b>Remove</b>	Deletes the checked machines from the host list.
<b>Get Machine Status</b>	Retrieves the status of the checked hosts.
<b>Import Network Profiles</b>	Allows you to select an XML file representing a network profile. You can save your network connection details to a file using the " <a href="#">Network Profile Manager Dialog Box</a> " on page <a href="#">1104</a> .
<b>Submit Changes</b>	Submits the settings in the right pane to the checked hosts.
<b>Cancel</b>	Clears the changes (agent settings, MI Listener settings, authentication settings, etc.) of the selected host to the state already saved to a file. For each tool, Load Generator, MI Listener, or Controller, a popup message prompts you to save the change .

<host list>	A list of the hosts that you defined with the <b>Add New Host</b> button, with the following columns: <ul style="list-style-type: none"><li>• <b>&lt;Check box.</b> In order to apply the changes from the right pane, you need to check the box for one or more hosts.</li><li>• <b>Name/IP.</b> After you add a new machine, you edit this field with the host name or its IP address. For the Controller you can specify localhost. For Monitor Over Firewall, you can enter "local machine key".</li><li>• <b>Type.</b> The component whose settings you want to configure. Select one from the drop-down list: <i>Load Generator</i>, <i>MIL Listener</i>, or <i>Controller</i>.</li><li>• <b>Network Profile.</b> A drop-down list showing the desired profile. Use the <b>Import Network Profiles</b> button to add more profiles to the list. The lower section of the right pane shows the Network Profile details.</li><li>• <b>Status.</b> (read-only). Displays the status (Successful or Failed) and a time stamp for submitting changes or getting machine status..</li></ul>
Agent ports	The port values for each of the components: <ul style="list-style-type: none"><li>• <b>Agent Port</b> The Load Generator m_agent listening port. <b>Default:</b> 54345</li><li>• <b>MIL to Controller Port.</b> MIL listening port from Controller. This option is not available for a Linux host. <b>Default:</b> 50500</li><li>• <b>MIL to LG port.</b> MIL listening port from Load Generator over firewall. If you change this port value, you should also change the port for the Load Generator over firewall machine using <b>-mil_port</b>. This option is not available for a Linux host. <b>Default:</b> 443</li><li>• <b>Agent Port for AutoLab</b> The Load Generator agent listening port for AutoLab. <b>Default:</b> 54245 (only available for Load Generator type hosts).</li></ul>

<b>Agent settings</b>	<p>These settings are hidden until you enable the <b>Use MI Listener</b> option. After you select this option you specify details about the MI Listener: <b>MI Listener Name</b>, <b>MI Listener Port</b>, <b>Local Machine Key</b>, <b>Username</b>, <b>Password</b>, <b>Sampling Interval</b>, and <b>Channel Type</b> (HTTP or TCP).</p> <ul style="list-style-type: none"><li>• <b>Proxy Settings</b> (Only visible for HTTP channel type): <b>Do not use Proxy</b>, <b>Take Proxy Settings from Machine</b>, or <b>Enter Proxy Settings Manually</b>.<ul style="list-style-type: none"><li>▪ For the <i>Enter Proxy Settings Manually</i> option: Name of proxy server, <b>Port</b>, <b>Username</b>, <b>Password</b>.</li></ul></li><li>• <b>Use Secure Connection (SSL)</b> Instructs the MI Listener to use SSL for its connection.<ul style="list-style-type: none"><li>▪ <b>Check Server Certificate</b>. The verification level : <b>None</b>, <b>Medium</b>, or <b>High</b>.</li><li>▪ <b>Private Key Password</b>. The private key for the SSL.</li></ul></li></ul>
<b>Authentication settings</b>	<ul style="list-style-type: none"><li>• <b>Do not use Authentication</b> Communicates with the Load Generator or MI Listener without authentication.</li><li>• <b>Use Authentication Settings</b> Communicates with the machine with authentication and secure communication channels. In this section you provide a path to your certificate files, or indicate a key in order to generate one. If you already provided this information in the Controller, it is shown here. For details, see the "<a href="#">"Authentication Settings Dialog Box" on page 1244</a>".</li><li>• <b>Use Secure Channels</b> Communicates with the machine with secure communication channels, indicated by a Security Key.</li></ul>

## Network and Security Manager - Command Line Tool

LoadRunner's new Network and Security Manager tool, **lr\_agent\_settings**, lets you update and configure agent-related settings on local and remote machines. It allows you to make these changes through a single command.

- Agent ports
- Agent settings
- Authentication
- Host security

To invoke this tool, you open a command line window and run the following file:

- Windows (LoadRunner, Standalone Load Generator, Standalone MI Listener, and Monitor Over Firewall): <LR path>\bin\lr\_agent\_settings.exe. **Note:** The user running the tool should have

write permissions to the LoadRunner installation folder.

- Linux (Standalone Load Generator): <LG path>\bin\lr\_agent\_settings.exe **Note:** You must have administrator privileges for running this on a Linux machine.

To configure the agent using the LoadRunner user interface, use the ["Network and Security Manager" on page 1105](#). If you want to automate your test and run it through the command line, use the **lr\_agent\_settings.exe**, tool described in this topic.

Below is a list of the command line arguments supported by this tool. To retrieve this list on the LoadRunner machine, type **lr\_agent\_settings.exe -usage** or **lr\_agent\_settings** with no arguments.

**Note:**

- \* LoadRunner currently supports basic and NTLM proxy authentication.
- \* You can only update the certificates on a remote machine, if:
  1. A secure connection was established using SSL.
  2. The client (the machine the tool is running on) was authenticated by the CA certificate on the remote load generator.
  3. Both of the above items were achieved by using certificates other than the defaults.

Option	Argument s	Description
Remote Update Options		
-remote_host	remote host name or IP	The names of the hosts to update with the new settings. To access the local machine, specify <b>localhost</b> or <b>127.0.0.1</b> . For multiple machines, repeat the command: e.g. <b>-remote_host host1 -remote_host host2</b> .
-remote_hosts_file	file name	The name of a file containing the host names or IP addresses. Separate multiple host names with a line break. For hosts over a firewall, specify a port. For example, <b>myserver1 </b> <b>myserver2:my_ofw_unix</b> <b>myserver2:my_ofw_1</b>
Agent Port Options		
-m_agent_port	port	The Load Generator m_agent listening port. <b>Default:</b> 54345

<b>-al_agent_port</b>	port	The Load Generator al_agent listening port. <b>Default:</b> 54245
<b>-mil_port_controller</b>	port	MIL listening port from Controller. This option is not available on Linux. <b>Default:</b> 50500
<b>-mil_port_lg</b>	port	MIL listening port from Load Generator over firewall. If you change this port value, you should also change the port for the Load Generator over firewall machine using <b>-mil_port</b> . This option is not available on Linux. <b>Default:</b> 443
<b>Load Generator Over Firewall Options</b>		
<b>-is_ofw</b>	0   1	Indicates whether to communicate over a firewall.
<b>-mil_name</b>	Host name or IP address	Changes the MI listener name or IP address from the side of the load generator over a firewall.
<b>-mil_port</b>	port number	Changes the port for the MI listener from the side of the load generator over a firewall. The default port is 443.
<b>-local_machine_key</b>	Local machine key	Changes the host symbol (or local machine key) for LG over a firewall, to establish a unique connection from behind the firewall.
<b>-mil_string</b>	MILname:local machine key	Changes the MI Listener name and the local machine key in one string separated by a colon, ":" ,
<b>-mil_username, -mil_passwd, -mil_domain</b>	username, password, domain	<p><b>-mil_username</b>. Changes the user name with which to connect to the MI Listener machine,</p> <p><b>-mil_passwd</b>. Changes the connection password.</p> <p><b>-mil_domain</b>. Changes the domain for MI Listener machine (required only if NTLM is used).</p>
<b>-sampling_interval</b>	sampling interval in seconds	Changes the sampling interval in seconds—the time the agent waits before retrying to connect to MI Listener machine. The Over Firewall load generator machine polls the MI Listener regularly to see if any Controller needs to use it for a test run. If no request is found, it closes the connection and waits this specified timeout period, before polling it again.
<b>-channel_type</b>	TCP   HTTP	Changes the connection type: HTTP or TCP.

<b>-proxy_name, -proxy_port</b>	hostname, port	<i>-proxy_name</i> . Changes the name of proxy server when using HTTP connection. <i>-proxy_port xxxx</i> : Changes the port of proxy server.
<b>-proxy_string</b>	proxy name:proxy port	Changes the proxy name and port in one string separated by a colon, ":",
<b>-proxy_username, -proxy_passwd, -proxy_domain</b>	username, password, domain	<i>-proxy_username</i> . Changes the user name with which to connect to the proxy server. <i>-proxy_passwd</i> . Changes the connection password.
<b>-use_ssl</b>	0   1	Changes the flag to connect using Secure Sockets Layer protocol.
<b>-private_key_pwd</b>	username, password, domain	Changes the password that is optionally required during SSL certificate authentication.
<b>-check_server_cert</b>	None   Medium   High	Indicates how to authenticate SSL certificates that are sent by the server.  <i>Medium</i> . verifies that the server certificates is signed by a trusted Certification Authority,
<b>Certificate Authentication Options</b>		
<b>-check_client_cert</b>	0   1	1. Enforce SSL connections only and check if the client certificate is trusted by the CA installed on the agent machine. <b>Note:</b> For monitoring over firewall, you set this flag to 1 on the server machine. For guidelines on determining which machine is the server, see <a href="#">MI Listener and Over Firewall Overview</a> .
<b>-CA_cert_file_name</b>	CA certificate file name	Installs a CA certificate locally. It overwrites the dat\cert\verify\cacert.cer file, but does not affect any configuration file.  <b>Note:</b> You need to generate a CA certificate before installing it. To generate the CA certificate, run <code>gen_ca_cert -common_name &lt;your_selected_common_name</code> , e.g. LoadRunner or HP> from the <b>bin</b> folder. Two files, cacert.cer and capvk.cer, will be generated in the current directory, for the CA certificate and private key. Store capvk.cer securely in a designated folder. Install cacert.cer as a CA certificate on all of your LR/PC installations.

<b>-cert_file_name</b>	full path of certificate file	Installs authentication certificate locally. It overwrites the dat\cert\verify\cacert.cer file, but does not affect any configuration file.  <b>Note:</b> This step assumes you already generated an SSL certificate ahead of time. Run gen_cert -common_name <your_selected_common_name, e.g. LoadRunner or HP> -CA_cert_file_name <CA_cert_file_full_path> -CA_pk_file_name <CA_private_key_file_full_path> from the <b>bin</b> folder to generate a certificate. You can use it across all of your LR/PC installations.
<b>-generate_new_cert_file - CA_private_key_file_name</b>	CA_private_key_file_full_path	Generates a new authentication certificate and installs it to dat\cert\cert.cer.  <b>Note:</b> A CA private key is mandatory to generate a self-signed certificates; The CA certificate will be read from dat\cert\verify\cacert.cer from current machine.
<b>-private_key_file_name</b>	private key file name	Sets the matching private key of the SSL certificate you installed with gen_ca_cert -common_name (see above). If you generate an SSL certificate using gen_cert or through the -generate_new_cert_file option in this tool, you can skip this step. You only need it if you use a certificate which does not include a private key in the certificate file, such as the <b>openssl</b> tool.
<b>Host Security Options</b>		
<b>-security_key</b>	security channel key	Changes the security key which is used to establish secure communication between an LG and Controller.
<b>-security_mode</b>	0   1	Changes the security mode.
<b>Restart Agent Options</b>		
<b>-restart_agent</b>		Restarts the magent or alagent. It automatically detects whether it is running as a service or process.  <b>Note:</b> If the agent is running as a process and you want to use the command line to restart it as a service, first use the <a href="#">"Agent Configuration Settings Dialog Box" on page 1243</a> to change between the Process and Service mode for the agent.
<b>Read Input Parameters</b>		

<b>-prm</b>	parameter file	<p>Retrieves the value of input parameters listed in a file. The prm file should have the following format:</p> <p><i>-mil_name MyHost1 -local_machine_key my_ofw_win -channel_type HTTP -proxy_name www.acme.com -proxy_port 8080.</i></p> <p><b>Notes:</b></p> <ul style="list-style-type: none"><li>• When using the -prm argument in the command line, all other arguments are ignored.</li><li>• The parameter file should only contain arguments for changing settings—not Remote Update arguments, <i>-remote_host</i> and <i>-remote_file</i>, which will be ignored.</li></ul>
-------------	----------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Common Examples

Below are some examples for using this tool to change settings for agent ports, LG over firewall settings, host security settings, certificate authentication, etc.

### **Set the agent proxy and port, and the MI Listener over a firewall**

```
lr_agent_settings.exe -proxy_name www.apache.com -proxy_port 8080  
lr_agent_settings.exe -m_agent_port 54888  
lr_agent_settings.exe -proxy_string web-proxy.sgp.hp.com:8080 (The string before ":" is proxy name, the string after ":" is proxy port)  
lr_agent_settings.exe -mil_string MyServer2:my_ofw_unix (The string before ":" is MIL name, the string after ":" is the local machine key)
```

### **Read parameters from a file**

```
lr_agent_settings.exe -prm C:\my_settings.prm
```

where the parameter file is a text file with the parameters you want to use to change the settings, e.g.

```
-mil_name MyServer3 -local_machine_key my_ofw_win -channel_type HTTP -proxy_name www.apache.com -proxy_port 8080
```

### **Remote updates**

```
lr_agent_settings.exe -remote_host MyServer1 -proxy_string www.apache.com:8080  
lr_agent_settings.exe -remote_host MyServer1 -prm C:\my_settings.prm
```

```
lr_agent_settings.exe -remote_host MyServer2:my_ofw_unix -prm C:\my_settings.prm  
(MyServer2:my_ofw_unix says the remote host is OFW, the name before ":" is MIL name, the  
string after ":" is local machine key)
```

```
lr_agent_settings.exe -remote_host localhost/127.0.0.1 -proxy_string www.apache.com:8080  
(Updates local host)
```

### ***Remote updates - multiple***

```
lr_agent_settings.exe -remote_host MyServer1 -remote_host vmlrnd192 -use_ssl 1
```

```
lr_agent_settings.exe -remote_host localhost -remote_host vmlrnd192 -use_ssl 1
```

```
lr_agent_settings.exe -remote_host MyServer1 -remote_host MyServer2:my_ofw_unix -prm  
C:\my_settings.prm
```

### ***Remote updates - multiple from file***

```
lr_agent_settings.exe -remote_file C:\remote_hosts.txt -proxy_string www.apache.com:8088
```

```
lr_agent_settings.exe -remote_file C:\remote_hosts.txt -prm C:\my_settings.prm
```

The file contains the hosts separated by line breaks":

**myserver1**  
**myserver2:my\_ofw\_unix**  
**myserver2:my\_ofw\_1**

### ***Restarting the agent***

```
lr_agent_settings.exe -is_ofw 1 -mil_string MyServer2:my_ofw_win -restart_agent
```

```
lr_agent_settings.exe -remote_host MyServer1 -remote_host MyServer2:my_ofw_unix -restart_  
agent
```

**Note:** If you encounter Access Denied warnings when restarting the service, see "[Agent Configuration Dialog Box](#)" on page 1241 for details.

## **SSL Utility**

The SSL Utility enables you to perform common OpenSSL functions from a user interface.

**Note:** To open the **SSL Utility**, click **Start > All Programs > HP Software > HP LoadRunner > Tools > SSL Utility**.

### **Converting Certificates**

The **Convert Certificate** tab of the **SSL Utility** enables you to convert certificates from PKCS #12 and X.509 formats to PEM format.

To convert a certificate to PEM format:

1. Open the **SSL Utility**, and click the **Convert Certificate** tab.
2. In the **Source certificate file** field, select the file that contains the certificate that you want to convert. The following file types are supported:

PKCS #12 files	.p12, .pxf
X.509 files	.cer, .crt, .der

3. In the **Import password** field, enter the password for decrypting the certificate file.
4. In the **PEM file** field, enter the name and location of the .pem file that will be created.
5. In the **PEM pass phrase** field, enter a password for the new certificate. If this is not specified, the certificate will not be password-protected.
6. From the **Source format** list, select the format of the original certificate that will be converted. This is automatically determined unless a file with a non-standard extension is selected.
7. Click **Convert**.

**Note:** This tab has the same functionality as the "x509" and "pkcs12" OpenSSL commands.

## Test Connection

The **Test Connection** tab of the **SSL Utility** enables you to capture the connection data from an SSL server and save it to a file <server name>\_<port number>\_ConnectionData.txt in the %temp% directory. Additionally, the file is displayed in a Notepad file when the test is completed.

To test a connection, enter the following on the **Test Connection** tab of the **SSL Utility**:

**Host/Port.** Specifies the host and port to connect to. If not specified, an attempt is made to connect to the local host on port 4433.

**Client certificate file.** The certificate to use if requested by the server. By default, a certificate is not required.

**Client key file.** The private key to use. If not specified the certificate file will be used.

**Password.**

**Note:** This tab has the same functionality as the "s\_client" OpenSSL command.

## Remove Certificate Encryption

This tab of the **SSL Utility** enables you to remove encryption from private key certificate.

To remove certificate encryption, enter the following on the **Remove Certificate Encryption** tab of the **SSL Utility**:

**Source PEM.** Name of the file containing encrypted private key and password.

**Target PEM.** Name of the file that will be unencrypted.

**Note:** This tab has the same functionality as the "pkcs12 -export" OpenSSL command.

## Scheduling Manual Scenarios

### *Scheduling Manual Scenarios Overview*

An important factor in the creation of a manual scenario is developing a test that accurately portrays user load behavior—the type of load and the timing of the load.

After you create a scenario, you schedule the scenario to start running at a specified time. You can limit the execution duration of the scenario or of a Vuser group within the scenario.

You can also stipulate how many Vusers to start and stop running within a certain time frame. You can specify whether LoadRunner should start or stop running all Vusers in a scenario simultaneously, or only a certain number of Vusers within a specified amount of time.

**Note:** Rendezvous points in a Vuser script interfere with a scheduled scenario run. If your script contains rendezvous points, your scenario will not run as scheduled. For details on rendezvous points, see "["Rendezvous Points" on page 1217](#)".

### *Scheduling by Scenario or Group*

After you have designed a manual scenario, you can schedule the participating Vuser groups/scripts to run as part of a scenario schedule.

You can schedule all the groups/scripts to run together on one schedule, or you can define a separate schedule for each Vuser group.

For details about manual scenario modes, see "["Manual Scenarios" on page 1040](#)".

#### **Scheduling By Scenario**

When you schedule **by scenario**, LoadRunner runs all the Vuser groups participating in the scenario simultaneously. That is, the schedule defined for running the scenario is applied to all the Vuser groups concurrently, and LoadRunner applies each action proportionately to all the Vusers groups.

For example, take a scenario that includes 3 participating Vuser groups as follows:

Group Name	Number of Vusers
Group1	10

Group2	20
Group3	30
<b>Total</b>	<b>60</b>

When scheduling by scenario, if the schedule instructs LoadRunner to load 30 Vusers when it starts running, LoadRunner loads a proportional number of Vusers from each group as follows:

Group Name	Number of Vusers
Group1	5
Group2	10
Group3	15
<b>Total</b>	<b>30</b>

**Note:** The same principle applies when viewing the scenario in percentage mode.

## Scheduling By Vuser Group

**Note:** For scenarios in Vuser group mode only.

When you schedule **by Vuser group**, each Vuser group participating in the scenario runs on its own separate schedule. That is, for each Vuser group, you can specify when to start running the Vuser group, how many Vusers in the group to start and stop running within specified time intervals, and how long the group should continue running.

## Schedule Run Modes

You can schedule a scenario to run according to the run-time settings defined in the Vuser groups, or you can let the groups run over and over again until the scenario schedule instructs them to stop running.

You can schedule a scenario to run in one of the following modes:

- **Real-world schedule.** (Default) The scenario runs according to a user-defined group of actions that simulate a real-world schedule of events. Vuser groups run according to the iterations defined in their run-time settings, but you can define how many Vusers to run at a time, how long Vusers should continue to run, and how many Vusers to stop running at a time.
- **Basic schedule.** All enabled Vuser groups run together on one schedule, each according to its own run-time settings. You can schedule how many Vusers to start running at a time, and how long they should run before stopping.

**Note:** You can change the default run mode in the **Tools > Options > Execution** tab.

The following table illustrates how the given schedule types run in real-world vs basic run mode:

Schedule by	Run Mode	
	Real-world	Basic
<b>Scenario</b>	All participating Vuser groups run together on one schedule. The scenario runs according to a user-defined group of actions that emulate a true-to-life schedule of events. You can schedule how many Vusers to start running at a time, how long to run the Vusers, and how many Vusers to stop running at a time.	All participating Vuser groups run together on one schedule, each according to its own run-time settings. You can schedule the Vusers to start and stop running simultaneously or gradually, and you can specify how long they should run before stopping.
<b>Group (Not applicable when viewing scenario in Percentage mode)</b>	Each participating Vuser group runs according to its own defined schedule that emulates a true-to-life schedule of events for that Vuser group. You can schedule when to start running the Vuser group, how many Vusers to run at a time, how long to run the Vusers, and how many Vusers to stop running at a time.	Each participating Vuser group runs according to its own schedule, each according to its own run-time settings. For each Vuser group, you can schedule how many Vusers in the group to start and stop running simultaneously or gradually, and you can specify how long they should run before stopping.

## **How to Define a Schedule for the Scenario - Workflow**

This task describes how to define a schedule for a scenario.


### **1. Prerequisite**

Make sure that a scenario is open, or create a new one, and that scripts have been selected for the scenario.

For more details, see "[How to Design a Manual Scenario](#)" on page 1045.

### **2. Define the schedule**

In the Scenario Schedule pane, select a schedule from the list, or define a new schedule by clicking **New Schedule** .




Define the schedule in the definition area as follows:

- (Optional) To rename the schedule, type a new name in the **Schedule Name** box and click **Save New Name**.
- Select the type of schedule: **Scenario** or **Group**. For details, see "[Scheduling by Scenario or Group](#)" on page 1116.
- Select a run mode: **Real-world** or **Basic**. For details, see "[Schedule Run Modes](#)" on page 1117.

**Note:** The default run mode for all schedules is **Real-world**. You can change the default to **Basic** in the **Tools > Options > Execution** tab.

### 3. Define actions for the schedule

The [Actions Grid](#) displays the default actions that correspond to the type of schedule you selected above.



For schedule action details, see "[Schedule Actions](#)" on page 1125.

- For details about how to add actions, see "[How to Add Actions to the Scenario Schedule](#)" on [the next page](#).
- For details about how to edit actions, see "[How to Edit Schedule Actions](#)" on page 1124.


#### 4. **Vuser group schedules only: Copy a group's schedule settings to other groups - optional**

When scheduling by Vuser group, you can copy a Vuser group's schedule settings to other Vuser groups.

**Note:** Schedule settings copied include the schedule run mode (basic or real-world) and the set of schedule actions.

##### **Example:**

To copy group\_1's schedule settings to group\_2, select **group\_2** in the Scenario Groups pane, click **Copy Schedule Settings From** , and select **group\_1**.



##### 5. Schedule a start time for the scenario - optional

In the Schedule Definition area, click the **Start Time** button and select when to start running the scenario.



#### How to Add Actions to the Scenario Schedule

**Note:** You can add actions to a **real-world schedule** only.

## Add an action to the schedule from the Actions grid

1. In the Action grid do one of the following:
  - To insert an action after a specific action, select the action and click **Add Action After** .
  - To add an action after the last action, double-click the last row in the Actions grid—marked by an asterisk (\*).
2. In the Add Action dialog box, define the new action. For schedule action details, see "[Schedule Actions](#)" on page 1125.
3. Click **Apply**.
4. To add another action while in the Add Action dialog box, click **Add Another Action** and repeat steps "[How to Add Actions to the Scenario Schedule](#)" on the previous page through "[How to Add Actions to the Scenario Schedule](#)" on the previous page.

## Add an action from the schedule graph

You can add **Start Vusers**, **Duration**, and **Stop Vusers** actions from the graph by splitting an action into two actions, or appending a new action after the last action in the graph.

1. Make sure that the graph is in Edit mode .
2. Select the line that represents the action that you want to split.

**Tip:** Selecting the action in the Actions grid highlights the corresponding line in the graph.


3. Click the **Split Action** button . The selected line splits in two. In the Actions grid, the original action splits into two equivalent actions, each representing half of the original action. For example:
  - Splitting a Duration action of 5 minutes results in two Duration actions of 2.5 minutes each.
  - Splitting a Start Vusers action that starts 20 Vusers results in two Start Vusers actions, each starting 10 Vusers.
4. (Optional) Edit each of the actions. For details, see "[How to Edit Schedule Actions](#)" on page 1124.

## Append an action after the last action


1. Make sure that the graph is in Edit mode .
2. In the graph toolbar, click **New Action** .

3. Append new actions as follows:


- **Start Vusers action.** Click the graph anywhere **above and to the right** of the endpoint of the last line of the graph.



- **Duration action.** Click the graph anywhere **directly to the right** of the endpoint of the last line of the graph.



- **Stop Vusers action.** Click the graph anywhere **below and to the right** of the endpoint of the last line of the graph.



4. Edit the actions. For details, see "[How to Edit Schedule Actions](#)" on the next page.

## How to Edit Schedule Actions

This task describes how to edit schedule actions, both in the Actions grid and from the schedule graph.

### Edit an action from the Actions grid

Double-click the action (or select it), click **Edit Action** , and edit the action as desired.

You can also edit other actions before closing the Edit Action dialog box. Click **Previous** or **Next** to navigate between the actions.

### Edit an action from the schedule graph

You can edit **real-world schedules** from the graph: you can edit Start Vusers, Stop Vusers, and Duration actions. When you edit actions from the graph, the action's details in the Actions grid are updated accordingly.

- Double-click the line in the graph representing the action you want to edit. Edit the action in the Edit Action dialog box that opens. Click **Previous** or **Next** to edit other actions.
- Make sure that the graph is in Edit mode , select the line in the graph, and drag it as follows:

Action	Modification
<b>Start Vusers</b>	To change <b>the number of Vusers</b> to start running: <ul style="list-style-type: none"><li>■ To start more Vusers, drag the diamond-shaped endpoint upwards.</li><li>■ To start fewer Vusers, drag the diamond-shaped endpoint downwards.</li></ul>
<b>Start Vusers</b>	To change <b>the time interval between starting Vusers</b> : <ul style="list-style-type: none"><li>■ To increase the time interval, drag the diamond-shaped endpoint to the right.</li><li>■ To decrease the time interval, drag the diamond-shaped endpoint to the left.</li></ul> <b>Note:</b> A vertical line indicates that the Vusers start running simultaneously.
<b>Duration</b>	<ul style="list-style-type: none"><li>■ To increase the duration between scheduled actions, drag the diamond-shaped endpoint to the right.</li><li>■ To decrease the duration between scheduled actions, drag the diamond-shaped endpoint to the left.</li></ul>
<b>Stop Vusers</b>	To change <b>the number of Vusers</b> to stop running: <ul style="list-style-type: none"><li>■ To stop fewer Vusers, drag the diamond-shaped endpoint upwards.</li><li>■ To stop more Vusers, drag the diamond-shaped endpoint downwards.</li></ul>

<b>Stop Vusers</b>	To change <b>the time interval between stopping Vusers</b> : <ul style="list-style-type: none"><li>■ To increase the time interval, drag the diamond-shaped endpoint to the right.</li><li>■ To decrease the time interval, drag the diamond-shaped endpoint to the left.</li></ul> <p><b>Note:</b> A vertical line indicates that the Vusers stop running simultaneously.</p>
--------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

**Tip:** To fine-tune any of the details of the selected action line, use the arrow keys on your keyboard, or edit the action in the Actions grid.

## Schedule Actions

A scenario schedule contains a series of actions that instruct the scenario when to start running a Vuser group, how to initialize Vusers, when to start and stop running Vusers, and how long to run an action.

The following sections describe the available schedule actions.

### Start Group

The Start Group action defines when to start running a Vuser group.

Options	Description
<b>Start immediately after the scenario begins</b> (Default)	LoadRunner starts running the Vuser group as soon as the scenario starts running.
<b>Start &lt;00:00:00&gt; (HH:MM:SS) after the scenario begins</b>	After the scenario starts running, LoadRunner waits the specified time (in hours, minutes, and seconds) before it starts running the Vuser group.
<b>Start when group &lt;group name&gt; finishes</b>	LoadRunner starts running the Vuser group immediately after the Vuser group specified in this option has finished running.

#### Note:

- The Start Group action is available for **group schedules only**, and always appears as each group's first schedule action.
- The Start Group action is always followed by the **Initialize** action.
- The Start Group action cannot be deleted.

### Initialize

The Initialize action instructs LoadRunner to prepare the Vusers so that they are in the Ready state and can run.

Options	Description
<b>Initialize all Vusers simultaneously</b>	LoadRunner initializes all the Vusers together before running them.
<b>Initialize XX Vusers every &lt;00:00:00&gt; (HH:MM:SS)</b>	LoadRunner initializes the specified number of Vusers gradually, according to the specified time interval (in hours, minutes, and seconds), before running them.
Initialize each Vuser just before it runs (Default)	LoadRunner initializes each Vuser just before it starts running. <b>Note:</b> This option is not available for group schedules when the <b>Wait for all groups to initialize</b> option is selected. For details, see <a href="#">Schedule Definition Area</a> .

**Note:**

- The Initialize action appears in the Actions grid for all schedule types.
- The Initialize action cannot be deleted.

## Start Vusers

The Start Vusers action instructs LoadRunner to start running Vusers.

Options	Description
<b>Start XX Vusers: Simultaneously (Default)</b>	LoadRunner runs the specified number of Vusers simultaneously.
<b>Start XX Vusers: YY Vusers every &lt;00:00:00&gt; (HH:MM:SS)</b>	LoadRunner runs the specified number of Vusers (XX) gradually. That is, LoadRunner runs YY Vusers, and waits the specified time (in hours, minutes, and seconds) before running another YY Vusers.

**Note:**

- LoadRunner starts running Vusers only when they have reached the Ready state.
- In a basic schedule, LoadRunner always runs **all** the Vusers, whether simultaneously or gradually. In a real-world schedule, you can select how many Vusers to start running.
- While a scenario is running, you can add Vuser groups/scripts to participate in the scenario. When starting the Vusers gradually, if you add a Vuser group to the scenario after all the original Vusers have already started running, the new group starts running immediately.

## Duration

The Duration action instructs LoadRunner to continue running the scenario in the current state, for

the specified amount of time.

Options	Description
<b>Run until completion</b>	<p>The scenario runs until all the Vusers have finished running.</p> <p><b>Note:</b> In real-world schedules, this option is available after the <b>first</b> Start Vusers action only, and if selected, causes all subsequent actions to be deleted.</p>
<b>Run for XX days and &lt;00:00:00&gt; (HH:MM:SS)</b>	<p>The scenario runs in its current state for the specified amount of time (in days, hours, minutes, and seconds) before continuing with the next action.</p> <p><b>Default:</b> 5 minutes.</p> <p><b>Note:</b> In a real-world schedule, if you select this option, and this Duration action is not followed by any other action, the scenario continues to run indefinitely.</p>
<b>Run indefinitely</b> (Basic schedule only)	The scenario runs indefinitely.

## Stop Vusers

The Stop Vusers action instructs LoadRunner to stop running Vusers.

Options	Description
<b>Stop xx Vusers: Simultaneously</b> (Default)	LoadRunner stops running the specified number of Vusers at once.
<b>Stop xx Vuser: YY Vusers every &lt;00:00:00&gt; (HH:MM:SS)</b>	LoadRunner stops running the specified number of Vusers gradually. That is, LoadRunner stops YY Vusers, and waits the specified time (in hours, minutes, and seconds) before stopping another YY Vusers, until all XX Vusers have stopped running.

## Add Action Dialog Box

This dialog box enables you to add actions to a real-world scenario schedule to simulate a more true-to-life schedule by which to run your scenario.

<b>To access</b>	<p>In the <b>Design</b> tab &gt; <b>Scenario Schedule</b> pane &gt; <b>Actions</b> grid, do one of the following:</p> <ul style="list-style-type: none"> <li>Double-click the last row in the Actions grid—marked by an asterisk (*).</li> <li>In the Actions grid, select the action after which you want to add a new action, and click <b>Add Action After</b> .</li> </ul>
------------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	<ul style="list-style-type: none"><li>Available for <b>real-world schedules only</b>.</li><li>You can add Start Vusers, Duration, and Stop Vusers actions only.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Define a Schedule for the Scenario - Workflow" on page 1118</a>
<b>See also</b>	<ul style="list-style-type: none"><li><a href="#">Actions Grid</a></li><li><a href="#">"Schedule Actions" on page 1125</a></li></ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	Resets the Add Action dialog box so that you can add another action. Available only after clicking <b>Apply</b> when adding an action.
	Adds the defined action to the Actions grid. Leaves the Add Action dialog box open, <b>in edit mode</b> , so that you can make changes to the action you added or add another action.
<b>&lt;Action details area&gt;</b>	The details of the new action. For details about the schedule actions, see <a href="#">"Schedule Actions" on page 1125</a> .
<b>Action type</b>	The type of action to add.

## Edit Action Dialog Box

This dialog box enables you to edit schedule actions.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>Double click an action in the Actions grid or in the interactive graph.</li><li><b>Design tab &gt; Scenario Schedule pane &gt; Actions grid/Schedule graph &gt; Edit Action</b> </li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>In the Actions grid, you can edit all actions.</li><li>In the interactive graph, you can edit Start/Stop Vusers and Duration actions only.</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li><a href="#">"How to Define a Schedule for the Scenario - Workflow" on page 1118</a></li><li><a href="#">"How to Edit Schedule Actions" on page 1124</a></li></ul>

<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">Actions Grid</a></li><li>• <a href="#">"Schedule Actions" on page 1125</a></li><li>• <a href="#">Interactive Schedule Graph</a></li></ul>
-----------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
< Previous	Displays the details of the previous/next action in the Actions grid.
Next >	
<Action details area>	Displays the current details of the selected action.
Action type	Displays the type of action selected.

## Scenario Schedule Pane

This pane enables you to define a schedule for running your scenario.

<b>To access</b>	Manual scenario > <b>Design</b> tab
<b>Relevant tasks</b>	<a href="#">"How to Define a Schedule for the Scenario - Workflow" on page 1118</a>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Scheduling Manual Scenarios Overview" on page 1116</a></li><li>• <a href="#">"Scheduling by Scenario or Group" on page 1116</a></li><li>• <a href="#">"Schedule Run Modes" on page 1117</a></li></ul>

User interface elements are described below:

UI Element	Description
<b>Actions grid</b>	Displays a list of scenario's schedule actions. See <a href="#">Actions Grid</a> .
<b>Interactive schedule graph</b>	Displays a graphical representation of the scenario schedule. The lines in the graph correspond to the actions defined in the Actions grid. See <a href="#">Interactive Schedule Graph</a> .
<b>Schedule definition area</b>	Displays the selected schedule's details. See <a href="#">Schedule Definition Area</a> .

## Service Level Agreements

## Service Level Agreements Overview

**Service level agreements (SLAs)** are specific goals that you define for your load test scenario. After a scenario run, HP LoadRunner Analysis compares these goals against performance related data that was gathered and stored during the course of the run, and determines whether the SLA passed or failed.

Depending on the measurements that you are evaluating for your goal, LoadRunner determines the SLA status in one of the following ways:

SLA Type	Description
<b>SLA status determined at time intervals over a timeline</b>	<p>Analysis displays SLA statuses at set time intervals over a timeline within the run. At each time interval in the timeline—for example, every 10 seconds—Analysis checks to see if the measurement's performance deviated from the threshold defined in the SLA.</p> <p>Measurements that can be evaluated in this way:</p> <ul style="list-style-type: none"><li>• <b>Average Transaction Response Time</b></li><li>• <b>Errors per Second</b></li></ul>
<b>SLA status determined over the whole run</b>	<p>Analysis displays a single SLA status for the whole scenario run.</p> <p>Measurements that can be evaluated in this way:</p> <ul style="list-style-type: none"><li>• <b>Total Hits per run</b></li><li>• <b>Average Hits (hits/second) per run</b></li><li>• <b>Total Throughput (bytes) per run</b></li><li>• <b>Average Throughput (bytes/second) per run</b></li></ul>

You can define and edit SLAs in the Controller or in Analysis.

To define SLAs in the Controller, see "[How to Define Service Level Agreements](#)" on the next page.

For details about defining SLAs in Analysis and viewing SLA information in Analysis reports, see the *HP LoadRunner Analysis User Guide*.

## Tracking Period

When you define an SLAs for measurements that are evaluated over a timeline, Analysis determines SLA statuses at specified time intervals within that timeline. The frequency of the time intervals is called the **tracking period**.

An internally-calculated tracking period is defined by default. You can change the tracking period by entering a value in the Advanced Options dialog box which Analysis plugs into a built-in algorithm to calculate the tracking period. For details, see "[Advanced Options Dialog Box](#)" on page 1134.

## How to Define Service Level Agreements

This task describes how to define service level agreements (SLAs).

You can define service level agreements (SLAs) which measure scenario goals over time intervals, or over a whole scenario run. For details, see "[Service Level Agreements Overview](#)" on the previous page.

See also "[Working with Analysis](#)" on page 1350.

**Tip:** For a use-case scenario related to this task, see "[How to Define Service Level Agreements - Use-Case Scenario](#)" on the next page.

### 1. Prerequisites

If you are defining an SLA for Average Transaction Response Time, your scenario must include a script that contains at least one transaction.

### 2. Run through the SLA wizard

In the Service Level Agreement pane, click **New** to open the Service Level Agreement wizard. For user interface details, see "[Service Level Agreement Wizard](#)" on page 1136.

- a. Select a measurement for the SLA.
- b. If you are defining an SLA for Average Transaction Response Time, select the transactions to include in your goal.
- c. (Optional) When evaluating SLA statuses over a timeline, select load criteria to take into account and define appropriate load value ranges for the load criteria. For an example, see "[How to Define Service Level Agreements - Use-Case Scenario](#)" on the next page.
- d. Set thresholds for the measurements.
  - o If the **Average Transaction Response Time** or **Errors per Second** exceed the defined thresholds, Analysis will produce a **Failed** SLA status.
  - o If **Total Hits per run**, **Average Hits (hits/second) per run**, **Total Throughput (bytes) per run**, or **Average Throughput (bytes/second) per run** are lower than the defined threshold, Analysis will produce a **Failed** SLA status.

### 3. Define a tracking period - optional

For measurements whose SLA statuses are determined over time intervals, you need to define the frequency of the time intervals, that is, the **tracking period**. For details, see "[Tracking Period](#)" on the previous page.

For user interface details, see "[Advanced Options Dialog Box](#)" on page 1134.

#### 4. Results

When analyzing your scenario run, HP LoadRunner Analysis compares the data collected from the scenario run against the SLA settings, and determines SLA statuses which are included in the default Summary Report.

For more information, see "[Working with Analysis](#)" on page 1350.

## **How to Define Service Level Agreements - Use-Case Scenario**

This use-case scenario describes how to define a service level agreement (SLA) for Average Transaction Response Time.

#### 1. Background

The administrator of HP Web Tours would like to know when the average transaction response time for booking a flight and searching for a flight exceeds a certain value. Assume that your scenario includes a script that includes the following transactions: **book\_flight** and **search\_flight**.

#### 2. Start the SLA wizard


In the Service Level Agreement pane, click **New** to open the Service Level Agreement wizard.

#### 3. Select the measurement for the SLA

On the Select a Measurement page, under **SLA status determined at time intervals over a timeline**, select **Average Transaction Response Time**.

#### 4. Select the transactions to evaluate in your goal

On the Select a Transaction page, select the transactions to be evaluated: **book\_flight** and **search\_flight**.



## 5. Select a load criterion and define appropriate ranges of load - optional

On the Select Load Criteria page, select the load criterion to take into account when evaluating the average transaction response time.

In this case, to see the effect that various quantities of Vusers running on the system has on the average transaction response time of each transaction, in the **Load Criteria** box, select **Running Vusers**.

Then set the value ranges for the running Vusers:

Consider less than 20 Vusers to be a light load, 20 – 50 Vusers an average load, and 50 Vusers or more a heavy load. Enter these values in the Load Values boxes.

**Note:**

- You can set up to three in-between ranges.
- Valid load value ranges are consecutive—there are no gaps in the range—and span all values from zero to infinity.

The screenshot shows a dialog box with the following settings:  
Load Criteria: Running Vusers  
Load Values:  
- Less than 20: checked, value 20  
- Between 20 and 50: checked, values 20 and 50  
- Greater than or equal to 50: checked, value 50

## 6. Set thresholds

On the Set Threshold Values page, you define the acceptable average transaction response times for the transactions, taking into account the defined load criteria.

In this case, define the same threshold values for both transactions as follows: for a light load, a reasonable average response time can be up to 5 seconds, for an average load, up to 10 seconds, and for a heavy load, up to 15 seconds.

Running Vusers			
Transaction Name	<20	≥20 and <50	≥50
book_flight	5	10	15
search_flight	5	10	15

**Tip:** To define the same thresholds for all the transactions, you can type the values in the table nearer the bottom of the Set Threshold Values page, and click **Apply to all transactions**.

## 7. Define a tracking period - optional

When SLA statuses for a measurement are determined at time intervals over a timeline, the frequency of the time intervals is determined by the **tracking period**.

This step is optional because an internally-calculated tracking period of at least 5 seconds is defined by default. You can change the tracking period in the Advanced Options dialog box:

- a. In the Service Level Agreement pane, click the **Advanced** button.
- b. Select **Tracking period of at least X seconds**, and select a tracking period. The time intervals are calculated by Analysis according to a built-in algorithm and as a function of the value you enter here.

### Example:

If you select a tracking period of 10, and the aggregation granularity for the scenario (defined in Analysis) is 6, then the tracking period is set to the nearest multiple of 6 that is greater than or equal to 10, that is, Tracking Period = 12.

For details, see "[Tracking Period](#)" on page 1130.

For user interface details, see "[Advanced Options Dialog Box](#)" below.

## 8. Results

When analyzing your scenario run, Analysis applies your SLA settings to the default Summary Report and the report is updated to include all the relevant SLA information.

For example, it displays the worst performing transactions in terms of defined SLAs, how specific transactions performed over set time intervals, and overall SLA statuses.

For more information, see the *HP LoadRunner Analysis User Guide*.

## **Advanced Options Dialog Box**

This dialog box enables you to define a tracking period for load test scenario.

<b>To access</b>	Design tab > Service Level Agreement pane >  Advanced
<b>Important Information</b>	The tracking period is calculated by Analysis according to a built-in algorithm and as a function of the value entered here.

<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Define Service Level Agreements" on page 1131</li><li>"How to Define Service Level Agreements - Use-Case Scenario" on page 1132</li></ul>
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>

User interface elements are described below:

UI Element	Description
<b>Internally calculated tracking period</b>	Analysis sets the tracking period to the minimum value possible, taking into account the aggregation granularity defined for the scenario. This value is at least 5 seconds. It uses the following formula: $\text{Tracking Period} = \text{Max (5 seconds, aggregation granularity)}$
<b>Tracking period of at least X seconds</b>	Determines the minimum amount of time for the tracking period. This value can never be less than 5 seconds. Analysis sets the tracking period to the nearest multiple of the scenario's aggregation granularity that is greater than or equal to the value (X) that you selected. For this option, Analysis uses the following formula: $\text{Tracking Period} = \text{Max(5 seconds, } m(\text{Aggregation Granularity}))$ where <b>m</b> is a multiple of the scenario's aggregation granularity such that <b>m (Aggregation Granularity)</b> is greater than or equal to <b>X</b> . <b>Example:</b> If you select a tracking period of X=10, and the aggregation granularity for the scenario is 6, then the tracking period is set to the nearest multiple of 6 that is greater than or equal to 10, that is, Tracking Period = 12.

## Goal Details Dialog Box

This dialog box displays the thresholds that were set for the selected SLA.

<b>To access</b>	<b>Design tab &gt; Service Level Agreement pane &gt;</b>  <b>Details</b>
<b>Important information</b>	If you defined load criteria as part of your SLA, the threshold values are displayed per the defined load value ranges.
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>


## Service Level Agreement Pane

This pane lists all the service level agreements (SLAs) defined for the scenario.

<b>To access</b>	<b>Design tab</b>
------------------	-------------------

<b>Relevant Tasks</b>	<ul style="list-style-type: none"><li>"How to Design a Goal-Oriented Scenario" on page 1043</li><li>"How to Design a Manual Scenario" on page 1045</li><li>"How to Define Service Level Agreements" on page 1131</li><li>"How to Define Service Level Agreements - Use-Case Scenario" on page 1132</li></ul>
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>

User interface elements are described below:

UI Element	Description
 New	Starts the Service Level Agreement wizard where you can define new goals for the load test scenario.
 Details	Opens the Goal Details dialog box which displays a summary of the details of the selected SLA.
 Edit	Opens the Service Level Agreement wizard where you can modify the goals defined in the SLA.
 Delete	Deletes the selected SLA.
 Advanced	Opens the Advanced Options dialog box where you can adjust the tracking period for measurements that are evaluated per time interval over a timeline. For more information, see "Tracking Period" on page 1130. For user interface details, see "Advanced Options Dialog Box" on page 1134.
<b>Service Level Agreement list</b>	Lists the SLAs defined for the scenario.

## Service Level Agreement Wizard

This wizard enables you to define goals or **service level agreements** (SLAs) for your load test scenario.

<b>To access</b>	Design tab > <b>Service Level Agreement</b> pane >  New
<b>Important information</b>	There are two modes for the Service Level Agreement wizard. The pages included in the wizard depend on the measurement that is selected. See the wizard maps below.

<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Design a Goal-Oriented Scenario" on page 1043</li><li>"How to Design a Manual Scenario" on page 1045</li><li>"How to Define Service Level Agreements" on page 1131</li><li>"How to Define Service Level Agreements - Use-Case Scenario" on page 1132</li></ul>
<b>Wizard map - Goal measured per time interval</b>	The "Service Level Agreement Wizard" on the previous page contains: <b>Welcome</b> > "Select a Measurement Page" below > ("Select Transactions Page" on the next page) > "Set Load Criteria Page" on page 1139 > "Set Threshold Values Page (Goal Per Time Interval)" on page 1141
<b>Wizard map - Goal measured over whole scenario run</b>	The "Service Level Agreement Wizard" on the previous page contains: <b>Welcome</b> > "Select a Measurement Page" below > "Set Threshold Values Page (Goal Per Whole Run)" on page 1142
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>

## Select a Measurement Page

This wizard page enables you to select a measurement for your goal.

<b>Important information</b>	<ul style="list-style-type: none"><li>General information about this wizard is available here: <a href="#">"Service Level Agreement Wizard" on the previous page</a>.</li><li>There are two modes for the Service Level Agreement wizard. The wizard pages that follow depend on the measurement that you select on this page. See the wizard maps below.</li></ul>
<b>Wizard map - Goal measured per time interval</b>	The "Service Level Agreement Wizard" on the previous page contains: <b>Welcome</b> > <a href="#">"Select a Measurement Page" above</a> > ("Select Transactions Page" on the next page) > "Set Load Criteria Page" on page 1139 > "Set Threshold Values Page (Goal Per Time Interval)" on page 1141
<b>Wizard map - Goal measured over whole scenario run</b>	The "Service Level Agreement Wizard" on the previous page contains: <b>Welcome</b> > <a href="#">"Select a Measurement Page" above</a> > "Set Threshold Values Page (Goal Per Whole Run)" on page 1142
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>

User interface elements are described below:

UI Element	Description
------------	-------------

<b>SLA status determined over the whole run</b>	Evaluates a single SLA status for the whole scenario run. Select one of the following measurements: <ul style="list-style-type: none"><li>• <b>Total Hits per run</b></li><li>• <b>Average Hits (hits/second) per run</b></li><li>• <b>Total Throughput (bytes) per run</b></li><li>• <b>Average Throughput (bytes/second) per run</b></li></ul>
<b>SLA status determined per time intervals over a timeline</b>	Evaluates SLA statuses at set time intervals within the run. Select one of the following measurements: <ul style="list-style-type: none"><li>• <b>Average Transaction Response Time</b></li><li>• <b>Errors per Second</b></li></ul> <p>The time intervals at which the SLA statuses are evaluated are known as the <b>tracking period</b>. For details, see "<a href="#">"Tracking Period" on page 1130</a>".</p>

## Select Transactions Page

This wizard page enables you to select transactions to evaluate as part of your goal.

<b>Important information</b>	<ul style="list-style-type: none"><li>• General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard" on page 1136</a>.</li><li>• This page is displayed only creating an SLA for Average Transaction Response Time.</li><li>• In order to define an SLA for Average Transaction Response Time, at least one of the Vuser scripts participating in the scenario must include a transaction.</li><li>• You can select multiple transactions using the CTRL key.</li></ul>
<b>Wizard map - Goal measured per time interval</b>	The " <a href="#">Service Level Agreement Wizard" on page 1136</a> contains: Welcome > " <a href="#">Select a Measurement Page</a> " on the previous page > (Select Transactions Page ) > Set Load Criteria Page > " <a href="#">Set Threshold Values Page (Goal Per Time Interval)" on page 1141</a>
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>

User interface elements are described below:

UI Element	Description
------------	-------------

<b>Available Transactions</b>	Lists the transactions in the Vuser scripts participating in the scenario. To move a script to the <b>Selected Transaction</b> list, select it and click <b>Add</b> .
<b>Selected Transactions</b>	Lists the transactions in the Vuser scripts participating in the scenario that have been selected for the SLA. To remove a script from this list, select it and click <b>Remove</b> .

## Set Load Criteria Page

This wizard page enables you to select load criteria to take into account when testing your goal.

<b>Important information</b>	<ul style="list-style-type: none"><li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1136.</li><li>This page is displayed only when defining an SLA that determines SLA statuses per time interval over a timeline.</li><li>In the next wizard step (Set Threshold Values page), you will set different thresholds per each of the load ranges that you select here.</li></ul>
<b>Wizard map - Goal measured per time interval</b>	The " <a href="#">Service Level Agreement Wizard</a> " on page 1136 contains: Welcome > " <a href="#">Select a Measurement Page</a> " on page 1137 > (" <a href="#">Select Transactions Page</a> " on the previous page) > "Set Load Criteria Page" above > " <a href="#">Set Threshold Values Page (Goal Per Time Interval)</a> " on page 1141
<b>See also</b>	<a href="#">"Service Level Agreements Overview"</a> on page 1130

User interface elements are described below:

UI Element	Description
<b>Load Criteria</b>	The relevant load criteria that you want to use. <b>Example:</b> If you want to see the impact of running Vusers on the measurement, select <b>Running Vusers</b> . To define an SLA without load criteria, select <b>None</b> .

<b>Load Values</b>	<p>Valid load value ranges are consecutive—there are no gaps in the range—and span all values from zero to infinity.</p> <ul style="list-style-type: none"> <li>• <b>Less than.</b> Enter the upper value for the lower range of values for the load criteria.</li> </ul> <p>The lower range is between 0 and the value you entered. It does not include the upper value.</p> <p><b>Example:</b> If you enter 5, the lower range of values for the load criteria is between 0 and 5, but does not include 5.</p> <ul style="list-style-type: none"> <li>• <b>Between.</b> The in-between range of values for the load criteria. Enter lower and upper values for this range. The lower range is included in this range; it does not include the upper value.</li> </ul> <p><b>Example:</b> If you enter 5 and 10, the in-between range of values for the load criteria is from 5 and up to, but not including, 10.</p> <p><b>Note:</b> You can set up to three in-between ranges.</p> <ul style="list-style-type: none"> <li>• <b>Greater than.</b> Enter the lower value for the upper range of values for the load criteria.</li> </ul> <p>The upper range includes values from the value you entered and on.</p> <p><b>Example:</b> If you enter 10, the upper range of values for the load criteria is from 10 and on.</p>
<b>Selected Measurement</b>	The measurement selected for the goal.

## Set Percentile Threshold Values Page

This wizard page enables you to select load criteria to take into account when testing your goal.

<b>Important information</b>	<ul style="list-style-type: none"> <li>• General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1136.</li> <li>• The Percentile SLA enables you to measure whether the percentage of transaction samples meets the defined threshold criteria.</li> <li>• You can enter a threshold value to 3 decimal places.</li> </ul>
<b>Wizard map - Goal measured over whole scenario run</b>	The " <a href="#">Service Level Agreement Wizard</a> " on page 1136 contains: Welcome > " <a href="#">Select a Measurement Page</a> " on page 1137 > ("Select Transactions Page" on page 1138) > " <a href="#">Set Percentile Threshold Values Page</a> " above
<b>See also</b>	<a href="#">"Service Level Agreements Overview"</a> on page 1130

User interface elements are described below:

UI Element	Description
<b>Selected Measurement</b>	The measurement selected for the goal.
<b>Percentile</b>	Percentage of transactions to measure against the configured threshold.
<b>Provide threshold value for all transactions</b>	To apply one set of threshold values to all transactions selected for the goal, enter the threshold value and click <b>Apply to all</b> . These values are applied to all the transactions in the Thresholds table at the bottom of the page.
<b>Transaction name</b>	The transaction from the scenario run.
<b>Threshold</b>	The threshold value for the selected transaction.

## **Set Threshold Values Page (Goal Per Time Interval)**

This wizard page enables you to set thresholds for the measurements you are evaluating in your goal.

<b>Important information</b>	<ul style="list-style-type: none"> <li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1136.</li> <li>If you defined load criteria in the "<a href="#">Set Load Criteria Page</a>" on page 1139, you must set thresholds per each of the defined load ranges. If you did not define load criteria, you set one threshold value. For Average Transaction response time, you set threshold values for each transaction.</li> </ul>
<b>Wizard map - Goal measured per time interval</b>	The " <a href="#">Service Level Agreement Wizard</a> " on page 1136 contains: Welcome > " <a href="#">Select a Measurement Page</a> " on page 1137 > (" <a href="#">Select Transactions Page</a> " on page 1138) > " <a href="#">Set Load Criteria Page</a> " on page 1139 > " <a href="#">Set Threshold Values Page (Goal Per Time Interval)</a> " above
<b>See also</b>	<a href="#">"Service Level Agreements Overview"</a> on page 1130

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Thresholds table>	<p>The thresholds for your goal. If you defined load criteria, enter thresholds for each range of values.</p> <p><b>Note:</b> If the maximum threshold value is exceeded during a particular time interval during the run, Analysis displays an SLA status of <b>Failed</b> for that time interval.</p>

<b>Apply to all</b> (Average Transaction Response Time goal only)	To apply one set of threshold values to all transactions selected for the goal, enter the threshold values in this table and click <b>Apply to all transactions</b> . These values are applied to all the transactions in the Thresholds table at the top of the page.  <b>Note:</b> Threshold values for selected transactions do not have to be the same. You can assign different values for each transaction.
<b>Selected Measurement</b>	The measurement selected for the goal.

## ***Set Threshold Values Page (Goal Per Whole Run)***

This wizard page enables you to set minimum thresholds for the measurements you are evaluating in your goal.

<b>Important information</b>	General information about this wizard is available here: <a href="#">"Service Level Agreement Wizard" on page 1136</a> .
<b>Wizard map - Goal measured over whole scenario run</b>	The " <a href="#">"Service Level Agreement Wizard" on page 1136</a> contains: Welcome > <a href="#">"Select a Measurement Page" on page 1137</a> > <a href="#">"Set Threshold Values Page (Goal Per Whole Run)" above</a>
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1130</a>

User interface elements are described below:

UI Element	Description
<b>Selected measurement</b>	The measurement selected for the goal.
<b>Threshold</b>	The minimum threshold value for the selected measurement.  <b>Note:</b> If the value of the measurement is lower than this threshold during the run, Analysis displays an SLA status of <b>Failed</b> for the entire run.

## **Multiple IP Addresses**

### ***Multiple IP Addresses Overview***

Application servers and network devices use IP addresses to identify clients. The application server often caches information about clients coming from the same machine. Network routers try to cache source and destination information to optimize throughput. If many users have the same IP address, both the server and the routers try to optimize. Since Vusers on the same load

generator have the same IP address, server and router optimizations do not reflect real-life situations.

LoadRunner's Multiple IP Address feature enables Vusers running on a single load generator to be identified by many IP addresses. The server and router recognize the Vusers as coming from different load generators and as a result, the testing environment is more realistic.

This feature can be implemented on Windows and Linux platforms with the following protocols: DNS, IMAP, Oracle NCA, Oracle Web Applications 11i, POP3, RTE, SAP-Web, Siebel-Web, SMTP, Web (HTTP/HTML), Web Services, and Windows Sockets.

## How to Add IP Addresses to a Load Generator

The following steps describe how to add IP addresses to a load generator.

### 1. Run the IP Wizard on the load generator

- **Windows:** LoadRunner includes an IP Wizard program that you run on Windows load generators to create multiple IP addresses. You add new IP addresses to a machine once and use the addresses for all scenarios.

Run the IP Wizard on the load generator to add a specified number of IP addresses.

For details, see "[IP Wizard](#)" on the next page.

- **Linux:** Manually configure the new IP addresses for Linux load generators.

### 2. Update the server's routing table with the new addresses

Once the client machine has new IP addresses, the server needs the addresses in its routing table, so that it can recognize the route back to the client. If the server and client share the same netmask, IP class, and network, the server's routing table does not require modification.

**Note:** If there is a router between the client and server machines, the server needs to recognize the path via the router. Make sure to add the following to the server routing table: route from the Web server to the router, and routes from the router to all of the IP addresses on the load generator.

Update the Web server routing table as follows:

- a. Edit the batch file that appears in the IP Wizard Summary screen. An example .bat file is shown below.

```
REM This is a bat file to add IP addresses to the routing table of a
server
REM Replace [CLIENT_IP] with the IP of this machine that the server
already recognizes
REM This script should be executed on the server machine

route ADD 192.168.1.50 MASK 255.255.255.255 [CLIENT_IP] METRIC 1
route ADD 192.168.1.51 MASK 255.255.255.255 [CLIENT_IP] METRIC 1
route ADD 192.168.1.52 MASK 255.255.255.255 [CLIENT_IP] METRIC 1
route ADD 192.168.1.53 MASK 255.255.255.255 [CLIENT_IP] METRIC 1
route ADD 192.168.1.54 MASK 255.255.255.255 [CLIENT_IP] METRIC 1
```

- b. For each occurrence of [CLIENT\_IP], insert your IP address instead.
- c. Run the batch file on the server machine.

### 3. Enable the Multiple IP Addresses feature from the Controller

Once you define multiple IP addresses, you set an option to tell the Controller to use this feature.

- a. In the Controller Design view, select **Scenario > Enable IP Spoofing**.

**Note:** You must select this option before connecting to a load generator.

- b. In the Controller's **Tools > Options > General** tab (Expert mode only), specify how the Controller should allocate the IP addresses: per process or per thread. For details, see "["Options > General Tab" on page 1178](#)".

## IP Wizard

This wizard enables you to create and save new IP addresses on Windows machines.

To access	Start > All Programs > HP Software > HP LoadRunner > Tools > IP Wizard
<b>Important information</b>	This wizard resides on each load generator. It enables you to create and save new IP addresses on Windows machines. The new addresses can be a range of addresses defined by the Internet Assignment Numbers Authority. They are for internal use only, and cannot connect to the Internet. This range of addresses is the default used by the IP Wizard.
<b>Relevant tasks</b>	<a href="#">"How to Add IP Addresses to a Load Generator" on the previous page</a>

### IP Wizard Welcome - Step 1 of 3

User interface elements are described below:

UI Element	Description
<b>Create new settings</b>	Enables you to define new IP settings on the load generator.
<b>Load previous settings from file</b>	Enables you to use an existing file with IP address settings.
<b>Restore Original Settings</b>	Restores original settings.

### IP Wizard - Step 2 of 3 - Optional

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>&lt;Web Server Address box&gt;</b>	If you have more than one network card, enables you to choose the card to use for IP addresses. This step enables the IP Wizard to check the server's routing table to see if it requires updating after new IP addresses are added to the load generator.

### IP Wizard - Step 3 of 3 - Optional

User interface elements are described below:

UI Element	Description
<b>Add button</b>	Opens the Add dialog box where you can add a new IP address. The Add dialog box contains the following options: <ul style="list-style-type: none"><li>• <b>Private Address Spaces.</b> Classes that represents the correct submask for the machine's IP addresses.</li><li>• <b>From IP.</b> Adds IP addresses starting with this number.</li><li>• <b>Submask.</b> IP addresses include two components, a <b>netid</b> and <b>hostid</b>. The submask determines where the netid portion of the address stops and where the hostid begins.</li><li>• <b>Number to add.</b> The number of IP addresses to add.</li><li>• <b>Verify that new IP addresses are not already in use.</b> Instructs the IP Wizard to check the new addresses. The IP Wizard adds only the addresses that are not already in use.</li></ul>
<b>Remove button</b>	Removes a selected IP Address.
<b>IP Address</b>	The IP addresses on the load generator machine.

<b>Subnet Mask</b>	The submasks of the IP addresses on the load generator machine.
<b>Number of IPs added</b>	The number of IP addresses added to the load generator machine.
<b>Finish button</b>	Click Finish to exit the IP Wizard. The IP Wizard will run a <b>netsh</b> batch file to update the NT device drivers with the new addresses.

## IP Wizard - Summary

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Summary area>	Displays a summary of the operations performed by the IP Wizard. Take note of the location of the <b>netsh</b> batch file (.bat). This is used to update the routing table, if necessary. See " <a href="#">How to Add IP Addresses to a Load Generator</a> " on page 1143.

# Configuring Terminal Services Settings

## *Terminal Services Overview*

You can use LoadRunner's Terminal Services Manager to remotely manage multiple load generators running in your load testing scenario on a terminal server. In addition, you can use a terminal server to overcome the limitation of being able to run only a single GUI Vuser on a Windows-based load generator. By opening a terminal server session for each GUI Vuser, you can run multiple GUI Vusers on the same application.

A terminal server client can have multiple terminal sessions running simultaneously. Using LoadRunner's Terminal Services Manager, you can select the number of terminals to be used in your scenario (provided that you have sufficient terminal sessions running), and the maximum number of Vusers that can be run per terminal. The Terminal Services Manager then evenly distributes the number of virtual users among the client sessions.

**Note:** This feature is not supported if the Controller and the load generators connect over a firewall. To configure terminal services on a load generator over a firewall, see "[How to Configure Terminal Sessions Over a Firewall](#)" on page 1148.


## *About Terminal Services*

Terminal services allows centralized management of computing resources for each client connected to the server, and provides each user with their own working environment. Using a terminal server client, you can operate in a server-based computing environment from a remote

machine. The terminal server transmits applications over the network and displays them via terminal emulation software. Each user logs on and sees only his individual session, which is managed transparently by the server's operating system independent of any other client session.

**Note:** Only users with administrator privileges can connect from the Controller to a local load generator via a terminal services session.

The following diagram illustrates how the LoadRunner components work together during a terminal session.



## How to Use the Terminal Services Manager

This task describes how to set up and use LoadRunner's Terminal Services Manager.

### 1. Prerequisite

Make sure that a load generator has been installed on the terminal services machine. For more information, see the *HP LoadRunner Installation Guide*.

### 2. Set up the LoadRunner agent on the load generator

Perform the following steps:

- a. Select **Start > All Programs > HP Software > HP LoadRunner > Advanced Settings > Agent Configuration**, or run `<LR>\launch_service\bin\AgentConfig.exe` to open the Agent Configuration dialog box.
- b. Select **Enable Terminal Services**, and click **OK**.
- c. Restart the LoadRunner Agent as a process by double-clicking the shortcut on the desktop, or from **Start > All Programs > HP LoadRunner > Advanced Settings > LoadRunner Agent Process**. You need to run the LoadRunner Agent as a process for each terminal session that you are running.

### 3. Launch a terminal client session

Be aware of the following:

- You must open a Terminal Client session for each terminal that you want to run Vusers on during the scenario.
- If you are connecting to an existing Terminal Services session, you need to open a Terminal Client session, log in to the session, and run the LoadRunner Agent as a process.

### 4. Distribute Vusers on the terminal server

In the Terminal Services tab of the Load Generator Information dialog box, select **Enable Terminal Services Manager** and enter information about the terminals and Vusers that you want to use. For more information, see "["Load Generator Configuration > Terminal Services Tab" on page 1094](#)".

## How to Configure Terminal Sessions Over a Firewall

This task describes how to configure a terminal sessions on a load generator that is located over a firewall. You configure the terminal sessions as independent virtual load generators. Each virtual load generator must have its own logical name.

### Prerequisite

If the LoadRunner Agent is not running as a process, select **Start > All Programs > HP Software > HP LoadRunner > Advanced Settings > Agent Process** to run it as a process.

### Configure the terminal sessions as independent load generators

Perform the following steps:

1. Select **Start > All Programs > HP Software > HP LoadRunner > Advanced Settings > Agent Configuration** to open the Agent Configuration dialog box.
2. Select **Enable Firewall Agent** and **Enable Terminal Services**.
3. Click **Settings** to open the Agent Configuration Over Firewall Settings dialog box.
4. In the Local Machine Key field, enter a logical virtual load generator name, for example, `machine_ofw`.
5. Click **OK**.
6. Create one or more terminal sessions on the load generator console machine.

Keep in mind the following:

- For each terminal session, run the agent configuration as above. For each session, specify a different Local Machine Key name, for example, `machine_ofw_1`, `machine_ofw_2`, and so on.
- If you stop the agent on a terminal session, you must reconfigure the settings for that particular

session before restarting the agent.

- When selecting the load generator for the scenario in the Controller, select the local machine key for each individual virtual load generator used.

## Configuring Network Virtualization Settings

### *Network Virtualization Overview*

HP LoadRunner integrates with Shunra Network Virtualization (NV) to help you test point-to-point performance of network-deployed products under real-world conditions. By installing this software on your load generator, you can introduce highly probable network effects such as latency, packet loss, and bandwidth. As a result of this, your scenario performs the test in a more realistic environment that better represents the actual deployment of your application.

When you choose a location in Shunra NV, the application knows the parameters for that city—you do not need to manually provide this information.

For more information about Shunra NV for HP Software, see <http://www.shunra.com/products/shunra-nv-hp-software>.

The most typical network effects which you can configure with the network virtualization software are:

- **Latency.** The **Latency** value you define represents the time in milliseconds that it takes an IP packet to cross the network. This is usually affected by geographical distance, the available bandwidth, the network load on the route between the two ends, and whether this is a terrestrial link or not.
- **Packet Loss.** The **Packet Loss** value you define represents the chance of losing IP packets while data travels through a network. Packets can get lost due to link faults or due to extreme network load.
- **Bandwidth.** The **Bandwidth** value you define represents the capacity of your network to transfer data.


You can create more meaningful results by configuring several Vuser groups with unique network effects, depending on its route or location. For example, you could define a location from New York to London and another one from Los Angeles to New York. For details, see ["Virtual Locations Overview" on page 1151](#).

Network virtualization starts and stops automatically as you start and stop a scenario. Network virtualization metrics are automatically collected during the scenario run in the Shunra Network Virtualization monitor.

Network virtualization can be used in conjunction with IP spoofing, secure channels, and firewalls.

You can also view the results in Analysis. Using the graphs, you can group metrics from different groups according to their locations. For information on grouping metrics, see ["Filtering and Sorting Graph Data" on page 1394](#) in the Analysis section.

The following diagram shows the steps required for running a scenario with network virtualization.




For complete details about this task, see "[How to Run a Scenario with Network Virtualization](#)" on page 1152.

## Virtual Locations Overview

LoadRunner allows you to define different locations for your network virtualization testing, which emulate conditions unique to specific geographic areas. For example, you can define a location from **London to New York** which emulates that network path.

You add locations in the Network Virtualization Settings dialog box. You can define global virtualization settings or configure the settings for each of the locations separately.



For details, see "[Network Virtualization Settings Dialog Box](#)" on page 1155.

In LoadRunner Analysis, you can group the scenario results by the virtual location name. For information on grouping metrics, see "[Filtering and Sorting Graph Data](#)" on page 1394 in the Analysis section.

## Excluding Machines from Network Virtualization

In some situations, you may need to exclude certain machines that may affect the virtualization emulation, from the network virtualization . A typical example is a software update server.

To exclude a machine, you configure the IP Filter settings of your network virtualization software. When you exclude a machine, their network effects will not be included in the network virtualization results.

Which machines should you exclude? Any machine that is emulated, may affect the results of the actual scenario during its run, (for example, the Controller) should be excluded. The following machines are excluded by default:

- MI Listener, and proxy server machines
- The Diagnostics Commander server
- A machine running SiteScope

The following are situations to consider excluding a machine from network virtualization:

- In a Multiprotocol scenario that includes a Web server and a database server; where information from the database server is not required as a part of the load test. In such a case, you would exclude the database server.
- Deployment and software upgrade servers.
- Servers that run and store scripts on a shared network drive.

## **How to Run a Scenario with Network Virtualization**

This task describes how to run a scenario using network virtualization and view the metrics in Analysis.

### **1. Prerequisites**

- a. Make sure that you have Shunra Network Virtualization (NV) for HP Software 9.0 or higher installed on your Controller and load generator machines. For details, see <http://www.shunra.com/products/shunra-nv-hp-software>.
- b. Make sure that you have Internet Explorer 8 or higher. Chrome and Firefox are not supported for Shunra Network Virtualization.
- c. Disconnect the load generators upon which you intend to perform network virtualization.

On the main Controller toolbar, click the **Load Generator** button  to open the Load Generators dialog box. If the load generator is connected, select it and click **Disconnect**.

### **2. Open the Network Virtualization Settings dialog box**

On the Controller toolbar, click the **Show Network Virtualization Settings** button  to open the dialog box. For details, see "[Network Virtualization Settings Dialog Box](#)" on page [1155](#).

### **3. Enable network virtualization and choose a virtualization method**

- a. In the Network Virtualization Settings dialog box, select **Enable Network Virtualization**.
- b. Select a method: Use the default **Per Group** to perform network virtualization per Vuser

group. This option performs network virtualization per load generator, where each machine can only emulate a single location. For compatibility with earlier versions of Shunra, select **Per Load Generator**.

#### 4. Set the global network virtualization settings

- a. In the Network Virtualization Settings dialog box, click **Global Settings** to define the global options for all network virtualizations. This opens the interface to the Shunra NV software.
- b. In the Shunra NV tabs, follow their configuration recommendations. For details, see <http://www.shunra.com/products/shunra-nv-hp-software>.
- c. In the **IP Filter** section, specify any machines that you may want to exclude from network virtualization for all locations. For details on which machines to exclude, see "Excluding Machines from Network Virtualization" on page 1151.

#### 5. Add locations

In the Network Virtualization Settings dialog box, click in the **Virtual Locations** list and add one or more location names. For location names, use the ANSI standard format. You cannot use the following characters: \ / : “ ? ‘ < > | \* % ^ , ! { } ( ) ; = #

To add a new location, type it in the next available line.

**Note:** For concept details about virtual locations, see "Virtual Locations Overview" on page 1151.

#### 6. Configure the network virtualization settings per location

- a. In the Network Virtualization Settings dialog box, select a location in the **Virtual Locations** list and click **Configure**. This opens the interface to the Shunra NV software.
- b. In the Shunra NV **Virtualization** tab, select a definition mode such as **Import from library** or **Custom**. If you select **Import from library**, Shunra automatically uses its built-in settings for the location you select. If you select **Custom**, you need to manually specify the network effects to apply to the location, such as latency, loss, and client bandwidth. These settings override the global settings.
- c. In the Shunra NV **Options** tab's **Bandwidth allocation** section, select **Share bandwidth between all users** unless you are testing mobile applications.
- d. In the **Options** tab's **IP Filter** box, specify all of the machines that you want to exclude from network virtualization for this location. For details on which machines to exclude, see "Excluding Machines from Network Virtualization" on page 1151.
- e. Repeat the above steps for each location.

#### 7. For per Group mode: Set a location for each group

- a. In the **Virtual Location** column, select a location. If you do not want to use network virtualization for a specific group, do not select a location.

- b. Repeat the above step for each group.

## 8. For per Load Generator mode: Set a location for each load generator

- a. On the main Controller toolbar, click the **Load Generator** button  to open the Load Generators dialog box.
- b. Select the load generator and click **Details**.
- c. Click the **Network Virtualization** tab, click the **Virtual Location** drop-down and select a location for the Load Generator. If you do not want to use network virtualization for a specific load generator, do not select a location.
- d. Repeat the above steps for each load generator.

## 9. Close the Network Virtualization Settings dialog box

Close the Network Virtualization Settings dialog box.

## 10. Initiate the network virtualization monitors

- a. In the bottom section of the Controller window, select the **Run** tab.
- b. In the **Available Graphs** pane, locate the **Network Virtualization** node. Double-click the metrics to monitor them. For details, see "[Shunra Network Virtualization Monitoring](#)" on page 1296.

**Note:** If a load generator is connected over a firewall, add monitors manually using the Monitor Over Firewall component. For details, see "[Monitors Over a Firewall](#)" on page 1233.

## 11. Filter the measurements by location - optional

To view graphs for a specific location:

- a. Click within a graph.
- b. Select **Set Filter/ Sort By** from the right-click menu to open the Graph Settings dialog box.
- c. In the **Filter condition** section, select the *Location* row, and specify the desired location.

To group the measurements by location:

- a. Click within a graph and select **Set Filter/ Sort By** from the right-click menu.
- b. In the **Group by** section, select *Location* in the **Available groups** pane.

- c. Click the right arrow to move it into the **Selected groups** pane.

## 12. Export the network virtualization setting - optional

In the Network Virtualization Settings dialog box, click **Export** to save the settings to a file for future use.

## 13. Save and run the scenario.


Complete all other steps required to set up your scenario and save it. The network virtualization settings are saved together with the scenario. Run the scenario in the normal way. Network virtualization starts and stops automatically with the scenario. When a scenario runs with network virtualization, it shows the icon  **Network Virtualization** in the status bar. View the metrics in the monitors that you added earlier.

## 14. View the metrics in HP LoadRunner Analysis

Network virtualization metrics are automatically collected during the scenario run. Open Analysis and view the network virtualization metrics. You can group them by location, and correlate the metrics with other data such as response time.

# Network Virtualization Settings Dialog Box

This dialog box allows you to configure your network virtualization settings.



To access	Controller toolbar >  Show Network Virtualization Settings button
Important information	<ul style="list-style-type: none"><li>To access this dialog box, you must have the Shunra Network Virtualization for HP software installed on your machine.</li></ul>

<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Run a Scenario with Network Virtualization" on page 1152</li><li>"How to Add a Load Generator to a Scenario" on page 1077</li><li>"How to Modify Load Generator Settings" on page 1083</li></ul>
<b>See also</b>	<ul style="list-style-type: none"><li>"Configuring Network Virtualization Settings" on page 1149</li><li>"Network Virtualization Overview" on page 1149</li></ul>

User interface elements are described below:

UI Element	Description
<b>Enable Network Virtualization</b>	Enables network virtualization per one of the following: <ul style="list-style-type: none"><li><b>Per Group.</b> Assigns network virtualization locations per group when working with manual scenarios. (Default)</li><li><b>Per Load Generator.</b> Assigns network virtualization locations per load generator.</li></ul>
<b>Global Settings</b>	Opens the Shunra Network Virtualization (NV) interface for defining the global setting for the virtualization. This includes packet capture information, record method, and IP filters on a global level, applied to all locations. For details, see the relevant third party software documentation.
<b>Configure</b>	Opens the Shunra NV interface for setting the virtualization properties and location options. These include imported parameters, latency and packet loss values, and client bandwidth. For details, see the relevant third party software documentation.
<b>Duplicate</b>	Adds a new location with settings identical to the selected entry.
<b>Delete</b>	Removes the selected location from the list.
<b>Import/Export</b>	Imports or exports network virtualization settings to or from an XML file.
<b>Location list</b>	A list of the locations to be used for network virtualization. To add new location, type in the next available line.
<b>Apply</b>	Applies all of the network virtualization settings without closing the dialog box.

## Running Load Test Scenarios

### Online Monitor Graphs

## Online Monitor Graphs Overview

You can view the data collected by the online monitors using the online monitor graphs.

### About Online Monitor Graphs

Online monitor graphs display performance measurements for those resources being monitored during scenario run. Each measurement is represented on the graph by a colored line. Information about the measurements is listed in the legend below the graph. The legend displays the measurements for the selected graph only.

For details about selecting monitor graphs and customizing the graph display area, see "[How to Display Online Monitor Graphs](#)" below.

For details about customizing graph layout and measurements, see "[How to Customize Online Graph and Measurement Settings](#)" on the next page.

### Viewing Monitor Data Offline

After monitoring resources during a scenario run, you can view a graph of the data that was gathered using HP LoadRunner Analysis. Analysis processes the data from the scenario run results files, and generates a graph for each measurement that was monitored.

For details about working with Analysis at the end of the scenario run, see the *HP LoadRunner Analysis User Guide*.

## How to Display Online Monitor Graphs

This task describes how to open other monitor graphs and customize the graph display area.

### Prerequisites

To see data in the online monitor graphs, the relevant monitoring environments must be configured. For details, see "[How to Set Up a Monitoring Environment](#)" on page 1259.

### Open a monitor graph

By default, LoadRunner displays the following graphs in the graph display area:

- **Running Vusers**
- **Transaction Response Time**
- **Hits per Second**
- **Windows Resources**

You can open other graphs one at a time, as follows:

#### Method 1

1. Select **Monitors > Online Graphs > Open a New Graph**, or right-click a graph and select **Open a New Graph**.
2. In the Open a New Graph dialog box, click the "+" in the left pane to expand the category nodes, and select a graph. You can view a description of the selected graph in the **Graph Description** box.
3. Click **Open Graph**, or drag the selected graph into the right pane of the Run view.

#### Method 2

In the graph tree on the left of the Run tab, click the "+" to expand the category nodes. Double-click a graph or, alternatively, select it and drag it to the graph display area on the right.

**Note:** If the graph tree is not displayed, select **View > Show Available Graphs**. To hide the graph tree view, select **View > Hide Available Graphs**.

#### Customize the graph display area - Optional

By default, LoadRunner displays four graphs in the graph display area.

To change the number of graphs displayed, right-click a graph in the graph display area and select **View Graphs** (or select **View > View Graphs**).

Do one of the following:

- Select the number of graphs to display from the options given
- Select **Custom Number** and enter a number of graphs to display.
- To display only one graph, double-click the graph displayed in the graph display area. To return to the previous view, double-click the graph again.

## How to Customize Online Graph and Measurement Settings

This task describes ways to customize online graphs and graph measurements.

### Configure the graph settings

You can customize:

- The type of graph display
- What to display on the x-axis and y-axis.

You can apply these settings to all graphs, or to a specific graph only.

To configure the graph settings, in the Run tab, select **Monitors > Online Graphs > Configure**, (or right-click a graph and select **Configure**).

For user interface details, see "[Graph Configuration Dialog Box](#)" on page 1161.

## Configure the measurement settings


You can customize the appearance and scale of measurements in a graph, and select whether they should be displayed in the graph or hidden from the graph.

In the Run tab, right-click a measurement in the graph or legend, and select **Configure**.

For user interface details, see "[Measurement Configuration Dialog Box](#)" on page 1163.

### Example: Measurement Scale

In the following example, the same graph is displayed with a scale of 1 and 10:



The actual graph values range from 0-1, as shown in the left graph. You can view the information more accurately using a larger scale for the display, as shown in the right graph. However, to obtain the actual values, you need to divide the displayed value by the scale. In the example above, the highest value shown in the graph is 5. Since the scale is 10, the actual value is 0.5.


The legend below the graph indicates the scale factor.

Color	Scale	Measurement	Machine	Max	Min	Avg	Std	Last
purple	10	Processor Queue Length (System)	zeus	3	1.823529...	0.705882...	1	
teal	1	File Data Operations/sec (System)	zeus	127.1463...	6.64241...	43.36583...	24.31799...	49.928041

scale factors

### Example: Shown/Hidden Measurements

In the following example, the first image displays a line for each of the four measurements. In the second image, the second measurement listed in the legend is hidden in the graph:



## How to Manage Online Graphs

The following sections describe ways to work with the online monitor graphs.

### Freeze graphs

You can pause a specific graph during a scenario run. Select the graph and select **Monitors > OnlineGraph > Freeze**, or right-click the graph and select **Freeze**. To resume, repeat the above action. When resumed, the graph displays the data for the paused period as well.

### Overlay graphs

You can merge or overlay the results of two graphs from the same scenario into a single graph. This enables you to compare several different measurements at once.

In the Run tab, right-click one of the online graphs you want to overlay, and select Overlay Graphs.

**Note:** The x-axis of both graphs must be the same measurement.

For details, see "[Overlay Graphs Dialog Box](#)" on page 1165.

### Export graphs to HTML

You can export graphs displayed on the Run tab to HTML format for offline viewing at a later stage. When you export to HTML, the legend is also displayed with the graph.

You can export a single graph or all graphs in the online monitor display.

#### Export a single graph

1. Right-click the graph and select **Export to HTML**.
2. Specify a path and filename for the exported graph/report.

## Graph Configuration Dialog Box



This dialog box enables you to customize the online graph settings.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• Select <b>Monitors &gt; Online Graphs &gt; Configure</b>.</li><li>• Right-click a graph and select <b>Configure</b>.</li></ul>
<b>Important information</b>	You can apply these settings to all graphs, or to a specific graph only.
<b>Relevant tasks</b>	<a href="#">"How to Customize Online Graph and Measurement Settings" on page 1158</a>

User interface elements are described below:

UI Element	Description
<b>Apply to all graphs</b>	Applies the dialog box settings to all graphs.
<b>Apply to selected graph</b>	Applies the dialog box settings to the selected graph.

<b>Bar Values Type</b>	If the <b>Bar</b> display type is selected, determines the type of value that will be displayed in the bar graph: <b>Average</b> , <b>Last Value</b> , <b>Minimum</b> , <b>Maximum</b> .
<b>Display Type</b>	The type of graph displayed: line graph or bar graph. By default, each graph is displayed as a line graph. <b>Note:</b> For the Network Delay graph, if you right-click the graph and select <b>View Segments</b> , you can view the network segments of the graph as an area graph or a pie graph.
<b>Graph Time</b>	Indicates the scale for a graph's x-axis when it is time-based. A graph can show 60 to 3600 seconds of activity. To see the graph in greater detail, decrease the graph time. To view the performance over a longer period of time, increase the graph time. The available graph times are: <b>Whole Scenario</b> , <b>60</b> , <b>180</b> , <b>600</b> , and <b>3600</b> seconds.
<b>Network Delay View</b>	Available for the Network Delay Time graph only: <ul style="list-style-type: none"><li>• <b>SubPaths</b>. Displays the delay measurements from the source machine to each of the nodes along the network path.</li><li>• <b>DNS name</b>. Displays the DNS names of the measurements displayed in the legend.</li></ul>
<b>Refresh Rate</b>	The interval at which the graph is refreshed with new data. By default, the graph is refreshed every five seconds. If you increase the refresh rate, the data is refreshed less frequently. <b>Note:</b> In a large load test, it is recommended to use a refresh rate of three to five seconds. This enables you to avoid problems with CPU resource usage.

<b>Time</b>	<p>Specifies how the graph displays the time (in seconds) on the x-axis:</p> <ul style="list-style-type: none"> <li><b>Don't Show.</b> Instructs LoadRunner not to display values for the x-axis.</li> <li><b>Clock Time.</b> Displays the absolute time, based on the system clock.</li> <li><b>Relative to Scenario Start.</b> Displays the time relative to the beginning of the scenario.</li> </ul> <p><b>Note:</b> If no step is running, clock time is displayed.</p> <p><b>Example:</b> In the left image below the time is not displayed on the x-axis. In the right image, the time is displayed.</p> <div style="display: flex; justify-content: space-around;"> <div style="text-align: center;">  <p><i>Don't Show</i></p> </div> <div style="text-align: center;">  <p><i>Clock Time</i></p> </div> </div>
<b>Y-Axis Scale</b>	<p>Displays graphs using the selected y-axis scale:</p> <ul style="list-style-type: none"> <li><b>Automatic.</b> Displays the default y-axis values.</li> <li><b>Maximum Y-Axis Value.</b> The maximum value for the y-axis.</li> <li><b>Minimum Y-Axis Value.</b> The minimum value for the y-axis.</li> </ul>

## Measurement Configuration Dialog Box

This dialog box enables you to configure settings for measurements in a graph. You can:

- Change line colors
- Configure a measurement's scaling
- Show/hide measurements
- View descriptions of the measurements

<b>To access</b>	In the Run tab, right-click a measurement in the graph or legend, and select <b>Configure</b> .
------------------	-------------------------------------------------------------------------------------------------

<b>Relevant tasks</b>	<a href="#">"How to Customize Online Graph and Measurement Settings" on page 1158</a>
-----------------------	---------------------------------------------------------------------------------------

User interface elements are described below:

UI Element	Description
<b>Configuration tab</b>	<ul style="list-style-type: none"><li><b>Color.</b> The color assigned to the selected measurement.</li><li><b>Scale.</b> The relationship between the y-axis and the graph's actual value.<ul style="list-style-type: none"><li><b>Autoscale.</b> Automatically scales the measurement by calculating the best ratio for displaying the graph. For some graphs, this option is not available.</li></ul></li></ul> <p><b>Default value:</b> Autoscale</p> <p><b>Example:</b> A scale of <b>1</b> indicates that the measurement's value is the value of the y-axis. If you select a scale of <b>10</b>, you must multiply the y-axis value by 10 to obtain the true value of the measurement.</p> <ul style="list-style-type: none"><li><b>Show / Hide.</b> The resource selected in the legend is shown/hidden in the graph.</li></ul> <p>By default, all resource measurements are shown in the graph. To show only a selected measurement, right-click the measurement, and select <b>Show Only Selected</b>.</p> <p><b>Note:</b> Alternatively right-click a measurement in the graph legend and select <b>Show/Hide</b>.</p>
<b>Description tab</b>	Information about the measurement: <ul style="list-style-type: none"><li><b>Machine.</b> Displays the name of the machine whose resources are being monitored.<p>Displayed only when a machine's resources are being monitored.</p></li><li><b>Description.</b> Displays a description of the selected measurement.<p>Also accessible by right-clicking a measurement in the legend and selecting <b>Description</b>.</p></li></ul>
<b>Machine</b>	The name of the machine whose resources are being monitored. <p><b>Note:</b> Displayed only when a machine's resources are being monitored.</p>
<b>Measurement</b>	The name of the selected measurement.
<b>Network Type</b>	Appears only when monitoring a network path.

## Open a New Graph Dialog Box

This dialog box enables you to open a new graph.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• Run tab &gt; Monitors &gt; Online Graphs &gt; Open a New Graph</li><li>• Right-click a graph and select Open a New Graph.</li></ul>
<b>Important information</b>	The graph selected in the graph display area will be replaced by the added graph.
<b>Relevant tasks</b>	<a href="#">"How to Display Online Monitor Graphs" on page 1157</a>

User interface elements are described below:

UI Element	Description
 Open Graph	Opens the selected graph and displays it in the graph tree view.
<b>Display only graphs containing data</b>	Select this option to view only those graphs that contain data. To view the entire list of online monitor graphs (even those that do not contain data), clear this option.
<b>Graph Description</b>	Displays a description of the selected graph
<b>Select Graph box</b>	Lists the online monitor graphs by category. To expand a category node, click the "+". <b>Tip:</b> Graph names displayed in blue contain data. <b>Note:</b> You can select only one graph at a time.

## Overlay Graphs Dialog Box

This dialog box enables you to merge or overlay the results of two graphs from the same scenario into a single graph. The merging enables you to compare several different measurements at once.

For example, you can make an overlaid graph that displays the Web Throughput and Hits per Second as a function of the elapsed time.

<b>To access</b>	In the Run tab, right-click one of the online graphs you want to overlay, and select <b>Overlay Graphs</b> .
------------------	--------------------------------------------------------------------------------------------------------------

<b>Important information</b>	<ul style="list-style-type: none"><li>In order to overlay graphs, the x-axis of both graphs must be the same measurement.</li><li>When you overlay the contents of two graphs that share a common x-axis, the left y-axis on the overlaid graph shows the current graph's values. The right y-axis shows the values of the graph that was overlaid.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Manage Online Graphs" on page 1160</a>

User interface elements are described below:

UI Element	Description
<b>Current Graph</b>	The name of the current graph.
<b>Select graph to overlay with</b>	The name of the graph to be merged with the current graph.  <b>Note:</b> The drop-down list displays only the active graphs that have a common x-axis with the current graph.
<b>Title of overlaid graph</b>	The title given to the overlaid graph.

## ***Available Graphs Tree***

The Available Graphs Tree displays the online monitor graphs.

**Tip:** Graph names displayed in blue contain data.

To select measurements to monitor in a particular graph, see the monitor configuration instructions for each specific monitor. For details, see ["How to Set Up a Monitoring Environment" on page 1259](#).

Graph	Description
<b>Running Vusers</b>	Provides information about the status of the Vusers running in the current scenario on all load generators. The graph shows the number of running Vusers, while the information in the legend indicates the number of Vusers in each state.
<b>User-Defined Data Points</b>	Displays the real-time values of user-defined data points. You define a data point in your Vuser script by inserting an <b>lr_user_data_point</b> function at the appropriate place ( <b>user_data_point</b> for GUI Vusers and <b>lr.user_data_point</b> for Java Vusers).
<b>Error Statistics</b>	Provides details about the number of errors that accrue during each second of the scenario run. The errors are grouped by error source—for example, the location in the script or the load generator name.

Graph	Description
<b>Vusers with Errors</b>	Provides details about the number of Vusers that generate errors during scenario execution. The errors are grouped by error source.
<b>Transaction Response Time</b>	Shows the average response time of transactions in seconds (y-axis) as a function of the elapsed time in the scenario (x-axis).
<b>Transaction Per Second (Passed)</b>	Shows the number of successful transactions performed per second (y-axis) as a function of the elapsed time in the scenario (x-axis).
<b>Transaction Per Second (Failed, Stopped)</b>	Shows the number of failed and stopped transactions per second (y-axis) as a function of the elapsed time in the scenario (x-axis).
<b>Total Transactions Per Second (Passed)</b>	Shows the total number of completed, successful transactions per second (y-axis) as a function of the elapsed time in the scenario (x-axis).
<b>Hits Per Second</b>	Shows the number of hits (HTTP requests) to the Web server (y-axis) as a function of the elapsed time in the scenario (x-axis). You can compare this graph to the Transaction Response Time graph to see how the number of hits affects transaction performance.
<b>Throughput</b>	Shows the amount of throughput on the Web server (y-axis) during each second of the scenario run (x-axis). Throughput is measured in bytes and represents the amount of data that the Vusers received from the server at any given second. You can compare this graph to the Transaction Response Time graph to see how the throughput affects transaction performance.
<b>HTTP Responses per Second</b>	Shows the number of HTTP status codes—which indicate the status of HTTP requests, for example, "the request was successful," "the page was not found"—(y-axis) returned from the Web server during each second of the scenario run (x-axis), grouped by status code. You can group the results shown in this graph by script (using the "Group By" function) to locate scripts which generated error codes.
<b>Pages Downloaded per Second</b>	Shows the number of Web pages (y-axis) downloaded from the server during each second of the scenario run (x-axis). This graph helps you evaluate the amount of load Vusers generate, in terms of the number of pages downloaded.
<b>Retries per Second</b>	Shows the number of attempted Web server connections (y-axis) as a function of the elapsed time in the scenario (x-axis). A server connection is retried when the initial connection was unauthorized, when proxy authentication is required, when the initial connection was closed by the server, when the initial connection to the server could not be made, or when the server was initially unable to resolve the load generator's IP address.

Graph	Description
<b>Connections</b>	Shows the number of open TCP/IP connections (y-axis) at each point in time of the scenario (x-axis). One HTML page may cause the browser to open several connections, when links on the page go to different Web addresses. Two connections are opened for each Web server.
<b>Connections per Second</b>	Shows the number of new TCP/IP connections (y-axis) opened and the number of connections that are shut down each second of the scenario (x-axis).
<b>SSLs per Second</b>	Shows the number of new and reused SSL Connections (y-axis) opened in each second of the scenario (x-axis). An SSL connection is opened by the browser after a TCP/IP connection has been opened to a secure server.
<b>Windows Resources</b>	Shows the NT and Windows 2000 resources measured during the scenario. The NT and Windows 2000 measurements correspond to the built-in counters available from the Windows Performance Monitor.
<b>UNIX Resources</b>	Shows the Linux resources measured during the scenario. The Linux measurements include those available by the rstatd daemon: average load, collision rate, context switch rate, CPU utilization, incoming packets error rate, incoming packets rate, interrupt rate, outgoing packets error rate, outgoing packets rate, page-in rate, page-out rate, paging rate, swap-in rate, swap-out rate, system mode CPU utilization, and user mode CPU utilization.
<b>SNMP</b>	Shows statistics for machines running an SNMP agent, using the Simple Network Management Protocol (SNMP). The x-axis represents the elapsed time. The y-axis represents the resource usage.
<b>Network Delay Time</b>	Shows the delays for the complete path between the source and destination machines (for example, the database server and Vuser load generator). The graph maps the delay as a function of the elapsed scenario time.
<b>Apache</b>	Displays statistics about the resource usage on the Apache server during the scenario run. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
<b>Microsoft IIS</b>	Shows server statistics as a function of the elapsed scenario time. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
<b>Microsoft Active Server Pages</b>	Displays statistics about the resource usage on the ASP server during the scenario run. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
<b>Oracle</b>	Displays information from Oracle V\$ tables: Session statistics, V\$SESSTAT, system statistics, V\$SYSSTAT, and other table counters defined by the user in the custom query.

Graph	Description
<b>SQL Server</b>	Shows the standard Windows resources on the SQL server machine. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
<b>Shunra Network Virtualization Graphs</b>	Graphs that show information about the Shunra Network Virtualization: Average Latency, Packet Loss, Average Throughput, Average Bandwidth Utilization, and Total Throughput. For details, see " <a href="#">Shunra Network Virtualization Monitoring</a> " on page 1296.
<b>Service Virtualization</b>	Shows statistics of the service virtualization, showing the <b>Operations</b> and <b>Services</b> graphs. For details, see " <a href="#">Service Virtualization Integration</a> " on page 1322.
<b>SiteScope</b>	Displays statistics about the resource usage on the SiteScope machine during the scenario run. The x-axis represents the elapsed time. The y-axis represents the resource usage.
<b>Flex</b>	Measures statistics related to Flex RTMP connections and throughput, as well as buffering time. For details, see " <a href="#">Flex Monitoring</a> " on page 1304.
<b>Real Client</b>	Shows statistics on the RealPlayer client machine as a function of the elapsed scenario time. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
<b>Media Player Client</b>	Shows statistics on the Windows Media Player client machine as a function of the elapsed scenario time. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
<b>Siebel Server Manager</b>	Shows the resource usage of your Siebel Server Manager server as a function of the elapsed scenario time.
<b>Citrix Server</b>	Displays statistics about resource usage on the Citrix server during the scenario run.
<b>IBM WebSphere MQ</b>	Shows the resource usage of IBM WebSphere MQ Server channel and queue performance counters as a function of the elapsed scenario time.
<b>Network Client</b>	Shows statistics for FTP, POP3, SMTP, IMAP, and DNS Vusers on the network client machine as a function of the elapsed scenario time.

## Configuring Scenario Options

### ***Configuring Scenario Options Overview***

Before you run a scenario, you can configure both the load generator and Vuser behavior for the scenario. Although the default settings correspond to most environments, LoadRunner allows you

to modify the settings to customize the scenario behavior. The settings apply to all future scenario runs and generally need to be set only once.

You configure these settings from the **Tools > Options** dialog box. Settings related to load generator behavior apply to all the load generators in a scenario.

**Note:** You can configure settings for an individual load generator that override the global settings for that particular load generator. For details, see "[How to Modify Load Generator Settings](#)" on page 1083.

Global scenario configuration settings are unrelated to the Vuser run-time settings. Run-time settings apply to individual Vusers or scripts and contain information about logging, think time, and the network, the number of iterations, and the browser. For information on setting run-time settings, see Run-Time Settings Overview.

## Expert Mode

Expert mode is intended to provide support personnel with access to system information. When you work in the Expert mode, the Controller dialog boxes contain additional options for fine tuning the Controller operation.

To activate the Expert mode, select **Tools > Expert Mode**.

To deactivate Expert mode, select **Tools** and clear the **Expert Mode** option.

## Run-Time File Storage Locations

When you run a scenario, by default the run-time files are stored **locally on each load generator** (the machine running the Vuser script). The default location of the files is in the temporary folder specified by the load generator's environment variables (on Windows, **TEMP** or **TMP**, and on Linux, **\$TMPDIR** or **\$TMP**). If no environment variable is defined, the files are saved to the **/tmp** folder.

Alternatively, you can store the run-time files on a **shared network**. A shared network drive is a drive to which the Controller and all the load generators in the scenario have read and write permission. If you select to save run-time files on a shared network drive, you may need to perform path translation. Path translation ensures that the specified results folder is recognized by the remote load generator. For details about path translation see "[Path Translation](#)" on the next page.

You select where to store run-time files in the **Tools > Options > Run-Time File Storage** tab. For details, see "[Options > Run-Time File Storage Tab](#)" on page 1182.

The primary run-time files are as follows:

Run-Time File Type	Description

<b>Vuser Script files</b>	When you run a Vuser, the Controller sends a copy of the associated Vuser script to the load generator. The script is stored in the load generator's temporary run-time folder. If you specify that all Vusers access their Vuser scripts directly at some shared location, no transfer of script files occurs at run time. This method often necessitates path translation. For details, see " <a href="#">"Path Translation" below</a> ". This method may be useful in either of the following situations: <ul style="list-style-type: none"><li>• The file transfer facility does not work.</li><li>• The Vuser script files are large and therefore take a long time to transfer. Remember that Vuser script files are transferred only once during a scenario.</li></ul>
<b>Result files</b>	While you run a scenario, the participating Vusers write their results to the temporary run-time file folder. After scenario execution, these result files are collated or consolidated—results from all of the load generators are transferred to the results folder. After collating the results, the temporary run-time folder is deleted. For user interface details, see " <a href="#">"Options &gt; Run-Time File Storage Tab" on page 1182</a> ".

## Path Translation

**Path translation** might be required when storing scripts and run-time data results from a scenario on a shared network drive (**Tools > Options > Run-Time File Storage** tab).

Path translation is a mechanism used by LoadRunner to convert a remote path name for the Controller so that all participating machines recognize the same network drive.

### Example 1

The scenario runs on a Windows-based machine and includes multiple Vusers running on both Windows-based and Linux load generators. One remote load generator may map the network drive as F, while another load generator maps the same drive as H. In a complex situation such as this, you need to ensure that all participating load generators recognize the same network drive.

### Example 2

The Scenario Groups/Scripts pane in the Design view contains a list of all the Vuser scripts associated with a scenario, and their locations. A script's location (path) is always based on the Controller machine's mapping of that location. If a load generator maps to the script's path using a different name, path translation is required.

For example, assume that the scenario is running on a Windows-based machine named **pc2**, and that a Vuser script is located on a network drive. The Controller machine maps the network drive as **m:\lr\_tests**. If the remote load generator hosting the Vusers also maps the path as **m:\lr\_tests**, no translation is necessary. However, if the remote machine maps the path as another drive or path, for example **r:\lr\_tests**, you must translate the path to enable the load generator to recognize the script location.

**Note:** If the Controller and load generator machines are all Windows machines, consider using the **Universal Naming Convention** method instead of manually adding path translation information. On Windows machines, you can tell the Controller to convert all paths to UNC, in

which case all the machines are able to recognize the path without requiring path translation. An example of UNC format is \\machine\_a\results.

## How to Configure Scenario Options

The following sections describe how to configure options that will be relevant for all your scenarios. You configure these options in the Options dialog box (**Tools > Options**).

### Configure timeout options

Select **Tools > Options > Timeout** tab and specify timeout values for commands related to the load generator. For user interface details, see "["Options > Timeout Tab" on page 1183](#)".

If the command is not executed successfully within the timeout period, the load generator status changes to **Error**.

### Configure Vuser run-time settings

Select **Tools > Options > Run-Time Settings** tab. You can specify:

- The Vuser quota for a scenario
- How to stop running Vusers
- Whether to use a seed number for random sequencing

For user interface details, see "["Options > Run-Time Settings Tab" on page 1182](#)".

### Configure general scenario options for Expert mode

Select **Tools > Options > General** tab to specify the following general scenario settings that apply when in Expert mode:

- Specify the folder for data table storage
- Disable collation of log files after a scenario run. For details, see "["How to Collate Scenario Run Results" on page 1222](#)".
- Enable multiple IP address allocation. For details, see "["Multiple IP Addresses" on page 1142](#)".

For user interface details, see "["Options > General Tab" on page 1178](#)".

Configure the default schedule run mode

Select **Tools > Options > Execution** tab. Under **Default Scheduler** select a default run mode. For user interface details, see "["Options > Execution Tab" on page 1177](#)".

For details about schedule run modes, see "["Schedule Run Modes" on page 1117](#)".

### Define a command to run after scenario results are collated

Select **Tools > Options > Execution** tab. Under **Post Collate Command**, enter a command to run after collating scenario results. For user interface details, see "["Options > Execution Tab" on page 1177](#)".

For more details about collating run results, see "[How to Collate Scenario Run Results](#)" on page [1222](#).

## Configure global run-time file storage options

Select **Tools > Options > Run-Time File Storage** tab, and specify where LoadRunner should save and store scenario run-time files collected on remote load generators:

- On the load generator
- On a shared network drive

For user interface details, see "[Options > Run-Time File Storage Tab](#)" on page [1182](#).

**Note:**

- LoadRunner applies these settings to all the load generators participating in a scenario. You can change the settings for individual load generators as described in "[How to Modify Load Generator Settings](#)" on page [1083](#).
- Storing the files on a shared network drive is not recommended as it increases network traffic and necessitates path translation. For details about path translation, see "[Path Translation](#)" on page [1171](#).

## Configure monitoring options

Select **Tools > Options > Monitors** tab, and configure the online monitoring settings. For user interface details, see "[Options > Monitors Tab](#)" on page [1178](#).

Configure debug information options (Expert mode only)

Select **Tools > Options > Debug Information** tab, and determine the extent of the trace to be performed during a scenario run. For user interface details, see "[Options > Debug Information Tab](#)" on page [1176](#).

Configure output display options (Expert mode only)

Select **Tools > Options > Output** tab, and configure how to display running Vusers on the Controller machine. For user interface details, see "[Options > Output Tab](#)" on page [1180](#).

## Path Translation Table

To translate a path from one Windows-based computer to another, or between Windows-based and Linux machines, you create an entry in the **Path Translation table**. This table contains a list of paths translated into formats that can be recognized by different machines.

Each line of the Path Translation table has the following format:

```
<controller_host> <controller_path> <remote_path> [<remote_host>]
```

where:

- **controller\_host** is the name or type of the machine that is running the Controller.

The value of **controller\_host** can be:

- **<hostname>**. The name of the machine running the Controller, for example, LOADPC1
- **win**. The Controller is running on a Windows-based computer
- **controller\_path** is the path of a specific folder—as recognized by the Controller. For example, if the folder **scripts** is located on the network drive **r**—as mapped by the Controller—type the path **r:\scripts** in the **controller\_path** field.
- **remote\_path** is the path of a specific folder—as recognized by the remote machine. For example, if the folder **scripts** is located on the network drive **n**—as mapped by the remote load generator—type the path **n:\scripts** in the **remote\_path** field.

If a Vuser on the remote Linux load generator recognizes the above path as **/m/tests**, you would type this path in the **remote\_path** field.

- **remote\_host** is the name or type of the remote load generator. For example, if all the remote machines are Linux workstations, you could type **Linux** in the **remote\_host** field. The options for the **remote\_host** field are the same as the options for the **controller\_host** field, listed above. The **remote\_host** parameter is optional.

## Examples

The examples below show the use of the Path Translation table for a Windows-based Controller called Merlin.

- **Example 1:** Vusers are running on a Windows 2003 machine, **Oasis**. Merlin maps the network drive as **f:**, while **Oasis** maps it as **g:\loadtest**.

```
merlin f:\ g:\loadtest\ Oasis
```

- **Example 2:** Vusers are running on a Linux machine, **Ultra**. Ultra maps the networks drive as **/u/tests/load**.

```
merlin f:\ /u/tests/load/ Ultra
```

- **Example 3:** The mapping of the network drive by the remote load generator **Jaguar**, is identical to the Controller's mapping, so no translation is required. This line can be excluded from the Path Translation table.

```
merlin n:\ n:\ Jaguar
```

- **Example 4:** All Windows-based Vuser load generators map the network drive as **m:\loadtest**.

```
merlin l:\mnt\ m:\loadtest\ win
```

merlin                    1:\mnt\  
                          win                    m:\loadtest\

## Options Dialog Box

This dialog box enables you to configure scenario options.

To access	Tools > Options
<b>Important information</b>	<p>The settings configured in this dialog box:</p> <ul style="list-style-type: none"><li>• Generally need to be set only once</li><li>• Apply to all future scenarios</li><li>• Apply globally to all the load generators in a scenario.</li></ul> <p><b>Note:</b> You can change the settings for individual load generators (see "<a href="#">How to Modify Load Generator Settings</a>" on page 1083). Individual load generator settings override global scenario settings.</p>
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options" on page 1172</a>

User interface elements are described below:

UI Element	Description
<b>Debug Information tab</b> (Expert mode only)	Enables you to determine the extent of the trace to be performed during a scenario run. For details, see " <a href="#">"Options &gt; Debug Information Tab" on the next page</a> ".
<b>Execution tab</b>	Enables you to configure the following miscellaneous scenario settings: <ul style="list-style-type: none"><li>• The default schedule run mode for a new scenario</li><li>• The command to run after collating scenario results</li></ul> For details, see " <a href="#">"Options &gt; Execution Tab" on page 1177</a> ".
<b>General tab</b> (Expert mode only)	Enables you to specify global settings for data table storage, log file collation, and multiple IP address allocation. For details, see " <a href="#">"Options &gt; General Tab" on page 1178</a> ".
<b>Monitors tab</b>	Enables you to configure the online monitoring settings. For details, see " <a href="#">"Options &gt; Monitors Tab" on page 1178</a> ".

<b>Output tab</b> (Expert mode only)	Enables you to configure how running Vusers are displayed on the Controller machine. For details, see " <a href="#">Options &gt; Output Tab</a> " on page 1180.
<b>Path Translation Table tab</b>	Enables you to perform path translation when storing result and script files stored on a shared network drive. For details, see " <a href="#">Options &gt; Path Translation Tab</a> " on page 1181.
<b>Run-Time File Storage tab</b>	Enables you to specify where LoadRunner should save and store the run-time files. <b>Default value:</b> On the current Vuser machine. For details, see " <a href="#">Options &gt; Run-Time File Storage Tab</a> " on page 1182.
<b>Run-Time Settings tab</b>	Enables you to specify scenario run-time settings. For details, see " <a href="#">Options &gt; Run-Time Settings Tab</a> " on page 1182.
<b>Timeout tab</b>	Enables you to specify timeout values for certain commands related to the load generator. For details, see " <a href="#">Options &gt; Timeout Tab</a> " on page 1183.

## Options > Debug Information Tab

This tab enables you to configure the settings to determine the extent of the trace to be performed during a scenario run.

To access	Tools > Options > Debug Information tab
<b>Important information</b>	<ul style="list-style-type: none"><li>This tab is available only when the Controller is operating in the Expert mode.</li><li>The debug information is written to the Output window.</li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options"</a> on page 1172
<b>See also</b>	<a href="#">"Output Window"</a> on page 1205

User interface elements are described below:

UI Element	Description
<b>Defaults</b>	Sets the default debug information settings.
<b>Keep temporary files</b>	The LoadRunner Agent and Controller create temporary files that collect information such as the parameter file sent to the Vuser, the output compilation file, and the configuration file. The Agent files are saved in <b>brr</b> folders in the <b>TMP</b> or <b>TEMP</b> folder of the Agent machine. The Controller files are saved in <b>Irr</b> folders in the <b>TMP</b> or <b>TEMP</b> folder of the Controller machine. At the end of the scenario, all these files are automatically deleted. When selected, this option instructs the Agent and Controller not to delete these files so that you can use them for debugging.

<b>Trace Flags</b>	<p>For debugging purposes, you can configure the type of trace performed by LoadRunner during the scenario run. Select the appropriate options to enable the detailed trace. The available trace flags are:</p> <ul style="list-style-type: none"><li>• <b>General</b></li><li>• <b>File Transfer</b></li><li>• <b>Incoming Communication</b></li><li>• <b>Outgoing Communication</b></li></ul> <p>The trace information appears in the log file located in the specified Agent log folder.</p> <p><b>Note:</b> Select only the flags relating to your problem. For example, if you encounter specific problems with the transfer of files, select the <b>File Transfer</b> flag.</p>
--------------------	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Options > Execution Tab

This tab enables you to configure miscellaneous scenario execution settings.

<b>To access</b>	<b>Tools &gt; Options &gt; Execution tab</b>
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options" on page 1172</a>
<b>See also</b>	<a href="#">"Schedule Run Modes" on page 1117</a>

User interface elements are described below:

UI Element	Description
<b>Default Scheduler</b>	<p>Enables you to set the default schedule run mode for new scenarios.</p> <ul style="list-style-type: none"><li>• <b>Real-world schedule.</b> Runs the scenario according to a real-world set of events</li><li>• <b>Basic schedule.</b> Runs a basic schedule, starting the Vuser, running the for a given amount of time, and stopping them.</li></ul> <p>For more details, see <a href="#">"Schedule Run Modes" on page 1117</a>.</p>
<b>Post Collate Command</b>	<p>Enables you to define a command that the Controller will run directly after it collates the results of a scenario run.</p> <p><b>Example:</b> You can define a command to run a customer application that runs the Analysis API to extract data.</p> <p><b>Note:</b> In the command, you can use the keyword, <b>%ResultDir%</b>, to refer to the scenario's results folder. (This keyword is not case sensitive.)</p>

## Options > General Tab

This tab enables you to specify global settings for data table storage, log file collation, and multiple IP address allocation.

To access	Tools > Options > General tab
<b>Important Information</b>	This tab is available only when the Controller is operating in Expert mode.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li><a href="#">"How to Configure Scenario Options" on page 1172</a></li><li><a href="#">"How to Add IP Addresses to a Load Generator" on page 1143</a></li></ul>

User interface elements are described below:

UI Element	Description
<b>Multiple IP address mode</b>	Allocates IP addresses when the multiple IP address option is enabled ( <b>Scenario &gt; Enable IP Spoofing</b> ). The Controller can allocate an IP address per process or per thread. Allocation per thread results in a more varied range of IP addresses in a scenario. <b>Note:</b> If the IP Spoofing is not enabled, this option is not available.
<b>Data tables global directory</b>	The network location for data tables used as a source for parameter values. <b>Note:</b> This setting is only required for scripts created with earlier versions of LoadRunner.
<b>Do not collate log files</b>	Instructs LoadRunner to collate only the result files, and not the log files.
<b>Override RDP file</b>	Instructs LoadRunner to override the settings in the RDP file and use the terminal server settings. This applies to RDP Vusers running on load generators for which the Terminal Service Manager is enabled. For details, see <a href="#">Options &gt; General Tab</a> . This option requires you to have Remote Desktop access to the load generator.

## Options > Monitors Tab

In this tab you can enable the Transaction monitor, configure the behavior of the transaction data, and set the data sampling rate, error handling, debugging, and frequency settings for the online monitors.

To access	Tools > Options > Monitors tab
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options" on page 1172</a>
<b>See also</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>

User interface elements are described below:

UI Element	Description
Defaults	Sets the default timeout values.
Debug	If <b>Display debug messages</b> is selected, debug-related messages are sent to the Output window. For the Network monitor the messages are sent according to the specified debug level (1 - 9).
Error Handling	Controls the way in which LoadRunner issues error messages: <ul style="list-style-type: none"><li>• <b>Send errors to the Output window.</b></li><li>• <b>Pop-up an error message box.</b></li></ul>
Send (Expert mode only)	<ul style="list-style-type: none"><li>• <b>Summary.</b> Sends a summary of the collected data back to the Controller. Use this option if the speed at which the data is transferred is significant to you.</li><li>• <b>Raw Data.</b> Sends all of the data in raw form back to the Controller. Sending the data in raw form saves time because the data does not need to be processed. However, since all of the data is being transferred to the Controller, it may cause more network traffic.</li></ul>
Transaction Data	Configures the behavior of data for the Transaction, Data Point, and Web Resource online graphs. <ul style="list-style-type: none"><li>• <b>Enable Transaction Monitor.</b> Enables the online Vuser Transaction monitor to start monitoring transactions at the start of a scenario.</li><li>• <b>Frequency.</b> The frequency, in seconds, at which the online monitor samples the data to produce the Transaction, Data Point, and Web Resource online graphs. For a small scenario, use a lower frequency, for example, <b>1</b>. For a large scenario, use a higher frequency, for example, <b>3 - 5</b>. The higher the frequency, the less network traffic there will be. The data is averaged for the frequency period defined, and only one value is sent to the Controller.</li></ul> <p><b>Default value:</b> 5 seconds</p> <p>For information on enabling and disabling the Transaction monitor and Web Page Diagnostics, see "<a href="#">Runtime and Transaction Monitoring</a>" on page 1266.</p> <p><b>Note:</b></p> <ul style="list-style-type: none"><li>• Disabling this option conserves resources.</li><li>• You cannot modify these settings during scenario execution; you must stop the scenario before disabling the monitor or changing its frequency.</li></ul>

<b>Resource Monitoring</b>	<p>Indicates the sampling rate for resource monitors.</p> <ul style="list-style-type: none"><li>• <b>Data Sampling Rate.</b> The sampling rate is the period of time (in seconds) between consecutive samples. Enter the rate at which LoadRunner samples the scenario for monitoring data. If you increase the sampling rate, the data is monitored less frequently. This setting applies to all graphs.</li></ul> <p><b>Default value:</b> 3 seconds</p> <p><b>Note:</b></p> <ul style="list-style-type: none"><li>• This data sampling rate is applied to all server monitors that are subsequently activated. It is not applied to server monitors that have already been activated. To apply the new data sampling rate to activated server monitors, save your scenario and reopen it.</li><li>• Each monitor has a different minimum sampling rate. If the default sampling rate or the rate set here is less than a monitor's minimum sampling rate, the monitor will sample data at intervals of its minimum sampling rate. For example, the minimum sampling rate for the Oracle Monitor is 10 seconds. If the sampling rate is set here at less than 10 seconds, the Oracle Monitor will continue to monitor data at 10 second intervals.</li></ul>
----------------------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Options > Output Tab

This tab enables you to configure how to display running Vusers on the Controller machine.

<b>To access</b>	<b>Tools &gt; Options &gt; Output tab</b>
<b>Important information</b>	This tab is available only when the Controller is operating in Expert mode.
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options" on page 1172</a>
<b>See also</b>	<a href="#">"Output Window" on page 1205</a>

User interface elements are described below:

UI Element	Description
<b>Defaults</b>	Sets the default output options.

<b>Configuration of the "Show Vuser" operation</b>	<p>Specifies how to handle the Vuser logs:</p> <ul style="list-style-type: none"> <li>• <b>Max. simultaneously displayed.</b> The maximum number of Vuser logs that may be displayed simultaneously. <b>Default value:</b> 10</li> <li>• <b>Refresh timeout (milliseconds).</b> How often the Vuser log should be refreshed. <b>Default value:</b> Every 1000 milliseconds</li> </ul>
<b>Delete Output window messages upon Reset</b>	When selected, clears all messages in the Output window when you reset a scenario.

## Options > Path Translation Tab

This tab enables you to perform path translation when storing result and script files on a shared network drive.

<b>To access</b>	<b>Tools &gt; Options &gt; Path Translation tab</b>
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options" on page 1172</a>
<b>See also</b>	<ul style="list-style-type: none"> <li>• <a href="#">"Run-Time File Storage Locations" on page 1170</a></li> <li>• <a href="#">"Path Translation" on page 1171</a></li> </ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>&lt;Path Translation table&gt;</b>	Displays a list of paths translated into formats that can be recognized by different machines. You can insert comments by typing the # symbol at the start of a line in the table. For details, see <a href="#">"Path Translation Table" on page 1173</a> .
<b>Convert to UNC</b>	When selected, LoadRunner ignores the path translation table and converts all paths to the Universal Naming Convention. <b>Note:</b> This option can be used only when the Controller and load generator machines are all Windows-based machines.
<b>Mode</b>	The read/write permissions for the <b>ppath.mnt</b> file which contains the path translation table.
<b>Path</b>	The path to the <b>ppath.mnt</b> file which contains the path translation table.

## Options > Run-Time File Storage Tab

This tab enables you to specify where LoadRunner should save run-time files.

To access	Tools > Options > Run-Time File Storage tab
<b>Important information</b>	The run-time file storage options described below apply to all the load generators in a scenario. To change the settings for an individual load generators see " <a href="#">Load Generator Configuration &gt; Run-Time File Storage Tab</a> " on page 1092.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li><a href="#">"How to Configure Scenario Options" on page 1172</a></li><li><a href="#">"How to Prepare a Scenario to Run" on page 1185</a></li></ul>
<b>See also</b>	<a href="#">"Run-Time File Storage Locations" on page 1170</a>

User interface elements are described below:

UI Element	Description
<b>Scripts and results stored</b>	Select one of the following options: <ul style="list-style-type: none"><li><b>On the current Vuser machine.</b> Saves the run-time files on the load generator that is running the Vuser script.<p>If you select this option, you must collate the results before you can perform any analysis. You can wait for LoadRunner to collate the results when you launch HP LoadRunner Analysis, or you can collate results by choosing <b>Results &gt; Collate Results</b>. Alternatively, select <b>Results &gt; Auto Collate Results</b> to automatically collate the results at the end of each scenario run.</p></li><li><b>On a shared network drive.</b> Saves the scenario results and/or the Vuser scripts on a shared network drive. A shared network drive is a drive to which the Controller and all the load generators in the scenario have read and write permission.<p>If you select this option, you may need to perform path translation. Path translation ensures that the specified results folder is recognized by the remote load generator. For information about path translation, see "<a href="#">"Path Translation" on page 1171</a>.</p></li></ul>

## Options > Run-Time Settings Tab

This tab enables you to specify scenario run-time settings relating to Vuser quotas, stopping Vusers, and the seed for random sequences.

<b>To access</b>	Tools > Options > Run-Time Settings tab
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>• <a href="#">"How to Configure Scenario Options" on page 1172</a></li> <li>• <a href="#">"How to Prepare a Scenario to Run" on page 1185</a></li> </ul>

User interface elements are described below:

UI Element	Description
Defaults	Sets the default run-time setting values.
Use random sequence with seed	<p>Allows LoadRunner to use a seed number for random sequencing. Each seed value represents one sequence of random values used for test execution. Whenever you use this seed value, the same sequence of values is assigned to the Vusers in the scenario. This setting applies to parameterized Vuser scripts using the <b>Random</b> method for assigning values from a data file. It also affects the random percentage of recorded think time (see Run-Time Settings Overview). Enable this option if you discover a problem when running the test and want to repeat the test using the same sequence of random values.</p> <p><b>Default:</b> 0</p>
Vuser Quota	<p>To prevent your system from overloading, you can set quotas for Vuser activity. The Vuser quotas apply to Vusers on all load generators.</p> <ul style="list-style-type: none"> <li>• <b>Number of Vusers that may be initialized at one time - all load generators.</b> The maximum number of Vusers the load generator can initialize at a time (when an Initialize command is sent).</li> </ul> <p><b>Default:</b> 999</p>
When stopping Vusers	<p>Controls how Vusers stop running when the <b>Stop</b> button is clicked.</p> <ul style="list-style-type: none"> <li>• <b>Wait for the current iteration to end before stopping.</b> (Default) The Vuser completes the iteration it is running before stopping. The Vusers move to the <b>Gradual Exiting</b> status and exit the scenario gradually.</li> <li>• <b>Wait for the current action to end before stopping.</b> The Vuser completes the action it is running before stopping. The Vusers move to the <b>Gradual Exiting</b> status and exit the scenario gradually.</li> <li>• <b>Stop immediately.</b> The Vusers stop running immediately. The Vusers move to the <b>Exiting</b> status and exit the scenario immediately.</li> </ul>

## Options > Timeout Tab

This tab enables you to specify timeout values for certain commands related to the load generator.

<b>To access</b>	Tools > Options > Timeout tab
------------------	-------------------------------

<b>Important information</b>	<p>LoadRunner enables you to set the timeout interval for commands and Vuser elapsed time.</p> <p>The command timeouts are the maximum time limits for various LoadRunner commands. When a command is issued by the Controller, you set a maximum time for the load generator or Vuser to execute the command. If it does not complete the command within the timeout interval, the Controller issues an error message.</p> <p>LoadRunner recognizes the fact that the number of active Vusers influences the timeout values. For example, 1000 Vusers trying to initialize will take much longer than 10 Vusers. LoadRunner adds an internal value, based on the number of active Vusers, to the specified timeout value.</p>
<b>Relevant tasks</b>	<a href="#">"How to Configure Scenario Options" on page 1172</a>

User interface elements are described below:

UI Element	Description
Defaults	Sets the default timeout values.
Command Timeout (seconds)	If <b>Enable timeout checks</b> is selected, this area defines how LoadRunner should monitor the status of load generators and Vusers after a command is issued by the Controller. If the load generator or Vuser does not complete the command within the timeout interval you specified, the Controller issues an error message. If <b>Enable timeout checks</b> is not selected, LoadRunner waits an unlimited time for the load generators to connect and disconnect, and for the Initialize, Run, Pause, and Stop commands to be executed.
Command Timeout: Load Generator	<ul style="list-style-type: none"><li><b>Connect.</b> The time limit that LoadRunner waits to connect to any load generator. If a connection is not successful within this time, the status of the load generator changes to <b>Failed</b>. <b>Default value:</b> 120 seconds.</li><li><b>Disconnect.</b> The time limit that LoadRunner waits to disconnect from any load generator. If a disconnection is not successful within this time, the status of the load generator changes to <b>Failed</b>. <b>Default value:</b> 120 seconds.</li></ul>

<b>Command Timeout: Vuser</b>	<ul style="list-style-type: none"><li><b>Init.</b> The timeout value for the Initialize command. <b>Default value:</b> 180 seconds.</li><li><b>Run.</b> The timeout value for the Run command. <b>Default value:</b> 120 seconds.</li><li><b>Pause.</b> The timeout value for the Pause command. <b>Default value:</b> 120 seconds.</li><li><b>Stop.</b> The timeout value for the Stop command. <b>Default value:</b> 120 seconds.</li></ul>
<b>Update Vuser elapsed time every</b>	The frequency at which LoadRunner updates the value displayed in the <b>Elapsed Time</b> column in the Vusers dialog box. <b>Default value:</b> 4 seconds. <b>Example:</b> If you select a Vuser and click the <b>Initialize</b> button, LoadRunner checks whether the Vuser reaches the <b>READY</b> state within 180 seconds (the default <b>Init</b> timeout period); if it does not, the Controller issues a message indicating that the <b>Init</b> command timed out.

## Before Running Your Scenario

### How to Prepare a Scenario to Run

This task describes steps to take before you start running your scenario.

For details on designing the scenario, see "[Designing Scenarios](#)" on page 1040.

#### Specify result file name and location

Select **Results > Results Settings**.

1. Enter a descriptive name for the result file.

This is especially useful for cross results analysis, in which LoadRunner superimposes the results of several scenario runs in a single graph and lets you compare the results of multiple scenario runs. Giving each run a descriptive name enables you to distinguish between the results of the multiple runs displayed later in the analysis graph.

2. Enter the full path to the folder where the result file will be stored. This depends on the run-time file storage options configured.


For details on setting **global** run-time file storage options, see "[Options > Run-Time File Storage Tab](#)" on page 1182. To set run-time file storage options for an **individual** load generator, see "[Load Generator Configuration > Run-Time File Storage Tab](#)" on page 1092.

- If you are using the default file storage setting (local machine), specify a folder in which to store all of the collated results after the scenario run.
  - If you specified a shared network drive as the file storage method, specify the folder to which Vuser groups should write during scenario execution.
3. Select the appropriate options for subsequent scenario runs.

**Note:**

- When comparing the results of scenario runs in Analysis, the graph displays all the result sets by name. For example, the image below displays the superimposed results sets of two scenario runs, **res12**, and **res15**.

When naming the results files, avoid using the same name when saving to different directories.



- You can use HP's Web-based test management program, HP Application Lifecycle Management, to store results to a project. For information, see "[Managing Scenarios Using Application Lifecycle Management](#)" on page 1229.

## Specify Scenario Run-Time Settings

You can instruct LoadRunner to allow an individual Vuser or the Vusers in a group to complete the iterations they are running before stopping, to complete the actions they are running before stopping, or to stop running immediately. For details, see "[Options > Run-Time Settings Tab](#)" on page 1182.

## Set up the monitoring environment - optional

LoadRunner enables you to view data generated during the scenario run using the online monitors. Before the run, specify the server machines that the Controller should monitor during the scenario run.

For details, see "[How to Set Up a Monitoring Environment](#)" on page 1259.

## Delete diagnostics log files from servers

- **Siebel Diagnostics:** Delete Siebel Diagnostics logs (\*.sarm files) from all servers involved in the load test.
- **Siebel DB Diagnostics:** Delete log files from all servers involved in the load test.
- **Oracle 11i Diagnostics:** Delete trace log files from all servers involved in the load test.

## Enable Automatic Result Collation - optional

If you are using the default file storage setting—local machine—prior to running the scenario you can enable auto-collation. As soon as the scenario run is complete, LoadRunner automatically collates the results from all the load generators and diagnostics mediators/servers.

**Note:** Alternatively, you can collate the results manually after the scenario run is complete. For details, see "[How to Collate Scenario Run Results](#)" on page 1222.

To enable automatic collation, select **Results > Auto Collate Results**. When this feature is enabled, **Auto Collate Results** is displayed in the status bar.



If you are working in Expert mode, you can disable the collation of the log files. Select **Tools > Options > General tab > Do not collate log files**.

To set a post-collation command, select **Tools > Options > Execution tab**, and enter the command in the **Post Collate Command** box. For details, see "[Options > Execution Tab](#)" on page 1177.

## Enable Auto Load Analysis- optional

To invoke HP LoadRunner Analysis as soon as the scenario is finished running, select **Results > Auto Load Analysis**. When this is enabled, **Auto Load Analysis** is displayed in the status bar.



## Schedule scenario - Optional

Define a schedule for the scenario. For details, see "[How to Define a Schedule for the Scenario - Workflow](#)" on page 1118.

Provide scenario summary information - optional

Select **Scenario > Summary Information**, and enter the scenario's summary information.

For details, see "[How to Define a Schedule for the Scenario - Workflow](#)" on page 1118.

### Set up the scenario to run MMS (Media Player)- optional

This protocol is only supported for replay.

- When running a scenario in controller for an MMS script the scenario may fail if the Run-time Network->Speed Simulation setting is not "Use maximum bandwidth", and the Miscellaneous->Multithreading setting is not "Run Vuser as a process".
- If Media Player scripts fail with the error: *Error -86801:Host access denied, <hostname>* not available or missing, add the **mms\_disable\_host\_check** function to the script.

### Set up the scenario to run GUI Vusers - optional

If you have integrated a QuickTest or Unified Functional Testing script into the scenario:

- Ensure that QuickTest or Unified Functional Testing is closed before running the scenario.
- In the Run-Time Settings for script dialog box, only the **General** categories and sub-categories (**General, Iterations, Miscellaneous, Think Time**) are relevant for QuickTest or Unified Functional Testing tests. The **Replay** options are not relevant.

**Note:** You can run only one GUI Vuser concurrently per machine.

## Set Results Directory Dialog Box

This dialog box enables you to set the location in which the Controller saves scenario run results.

To access	Results > Results Settings
<b>Important information</b>	If you have an open connection to an HP ALM project, the Controller saves the results to a test set. You can also save the results directly to disk using the standard file system.
<b>Relevant tasks</b>	<a href="#">"How to Prepare a Scenario to Run" on page 1185</a>

User interface elements are described below:

UI Element	Description
<b>Automatically create a results directory for each scenario execution</b>	Instructs LoadRunner to create a unique results folder for each scenario run. By default, the result names are <b>res1</b> , <b>res2</b> , <b>res3</b> , and so on.

<b>Automatically overwrite existing results directory without prompting for confirmation</b>	Instructs LoadRunner to automatically overwrite previous result sets, without prompting the user.
<b>Directory</b>	A location in the file system under the Results folder, to which the Controller should save the results.  <b>Note:</b> Do not specify an admin/administrator folder, as non-admin users without sufficient permissions may be unable to write to such a folder.
<b>File System</b> (only when connected to HP ALM).	Displays the default LoadRunner folder path.
<b>HP ALM</b> (only when connected to HP ALM)	Enables you to save the results to an Application Lifecycle Management test set.
<b>Results Name</b>	Specify a name for the run results. LoadRunner allows you to give descriptive names to each result set. This is especially useful for cross results analysis, in which LoadRunner superimposes the results of several scenario runs in a single Analysis graph and lets you compare the results of multiple scenario runs. The descriptive graph names enable you to distinguish between the results of the multiple runs.
<b>Results Path</b>	Displays the location for the results as specified in <b>Results Name</b> and <b>Directory</b> . Avoid using the same name with different paths. Only the names appear on the Analysis graphs. If the result names are identical it will be difficult to distinguish between the runs.

## Summary Information Dialog Box

This dialog box enables you to provide a detailed description of the scenario.

<b>To access</b>	<b>Scenario &gt; Summary Information</b>
<b>Relevant tasks</b>	<a href="#">"How to Prepare a Scenario to Run" on page 1185</a>

User interface elements are described below:

UI Element	Description

<b>Author</b>	The name of the scenario's author
<b>Description</b>	A description of the scenario
<b>Scenario Path</b>	The name and location of the scenario definition file (.lrs)
<b>Subject</b>	A subject name or short title for the scenario

## Running Scenarios

### *Running Scenarios Overview*

After planning, designing and scheduling your scenario, you run it to create load on your application and to test its performance.

#### ***Before run***

When running a manual scenario in Percentage mode, you can change the way LoadRunner loads the Vusers. By default, when running a group assigned to use **All Load Generators**, the Controller calculates the number of Vusers per load generator, and ramps up all Vusers, one load generator after another. If the initialization section uses a lot of resources, this may affect the performance on the load generators. LoadRunner allows you to distribute the Vusers in a round-robin fashion.

- For Vusers in groups configured to use **All Load Generators** LoadRunner uses a round-robin method to ramp up the groups between all of the load generators.
- For all Vusers in a group not configured to run to use **All Load Generators**, LoadRunner uses a round-robin method to ramp up the Vusers between all of the group's load generators.

For details on how to enable round-robin ramp up, see "[How to Run a Scenario](#)" on the next page.

#### ***Start of run***

When you instruct LoadRunner to begin the scenario run, the Controller checks the scenario configuration information, invokes the applications that were selected to run with the scenario, and then distributes each Vuser script to its designated load generator. When the Vusers are ready, they start running their scripts.

As the scenario starts, in the Scenario Groups pane you can watch Vusers gradually start running.

#### ***During run***

During the scenario run, you can see a synopsis of the running scenario in the Scenario Status pane. You can also drill down to see which Vuser actions are causing the application problems.


The Controller's online graphs display performance data collected by the monitors. You use this information to isolate potential problem areas in your system.

## **End of run**

The scenario ends when all the Vusers have completed their scripts, when the duration runs out, or when you terminate it.

At the conclusion of the test run, the Scenario Status pane shows the **Down** status. This indicates that the Vusers have stopped running.

## **How to Run a Scenario**



This task describes how to run a scenario.

### **1. Prerequisite**

Open an existing scenario, or design a new one.

- To design a manual scenario, see "[How to Design a Manual Scenario](#)" on page 1045.
- To design a goal-oriented scenario, see "[How to Design a Goal-Oriented Scenario](#)" on page 1043.

### **2. Prepare to run the scenario**

Before you run the scenario, specify a location for the scenario results and other run-time related settings. For details, see "[How to Prepare a Scenario to Run](#)" on page 1185.

### **3. Set the ramp up method to round-robin - optional**

To enable the round-robin ramp up, search for the `wlrun7.ini` file, located in the `%windir%`. In the **[ScenarioDesign]** section, set the **DistributionByHostsInPercentageMode** flag to 1. For details, see "[Running Scenarios Overview](#)" on the previous page.

### **4. Run the scenario**

In the Run tab, click the **Start Scenario** button to begin running the scenario. The scenario runs according to its defined schedule.

### **5. Manually control the behavior, addition, and stopping of Vusers during the scenario run - optional**

You can do the following during the scenario run:

**Note:** For a use-case scenario that explains the differences between the following options, see "[Control Vusers During a Scenario Run - Use-Case Scenario](#)" on page 1194.

- **Control the behavior of Vuser groups.** You can initialize, run, and stop Vuser groups during the scenario run.

To initialize, run, or stop an entire Vuser group, select the group in the Scenario Groups pane, and click the desired button on the main Controller toolbar:

- **Initialize Vusers.**
- **Run Vusers.**
- **Stop Vusers immediately.**
- **Stop Vusers gradually.**

- **Run or stop individual Vusers.** You can run or stop specific Vusers within a Vuser group. For user interface details, see "[Vusers Dialog Box](#)" on page 1072.
- **Initialize/Run additional Vusers, or stop currently running Vusers.** You can manually control the addition of new Vusers to a running scenario, as well as stop running Vusers. For user interface details, see "[Run/Stop Vusers Dialog Box](#)" on page 1210.

## 6. View a log containing run-time information about each running Vuser - Optional

For user interface details, see "[Vuser Script Log](#)" on page 1216.

## 7. Release Vusers from a rendezvous before the Controller releases them - Optional

For more information, see "[Rendezvous Points](#)" on page 1217.

## 8. Log execution notes during the scenario run - Optional

The Controller provides you with a dialog box in which you can log comments while a scenario is running. To open the dialog box select **Scenario > Execution Notes**. The notes are automatically saved by clicking **OK** to close the dialog box.

## 9. Monitor the scenario - optional

During the scenario run, you can view data collected by the online monitors using the online monitor graphs. If you did not set up the monitors before you started the run, you can do so during the run. The data collected by the monitors can be viewed using the LoadRunner online graphs.

- For details about setting up the online monitors, see "[How to Set Up a Monitoring Environment](#)" on page 1259.
- For details about viewing the monitor graphs, see "[Online Monitor Graphs](#)" on page 1156.

## 10. Collate run results

If you are using the default file storage setting—local machine, when the scenario run is complete, the run results must be collated or consolidated in preparation for result analysis. If LoadRunner is not set up to collate the results automatically upon completion of the run, you need to collate the results manually after the run.

Select **Results > Collate Results > Collate Results**. For details, see "[How to Collate Scenario Run Results](#)" on page 1222.

For details about result collation, see "[Collating Run Data](#)" on page 1221.

## **Initialize, Run, or Stop Vuser Groups - Use-Case Scenario**

This use-case scenario describes how David can manipulate the behavior of the Vuser groups during the scenario run, irrespective of their defined schedules. The examples will show how he can initialize, run, and stop all the Vusers in a Vuser group simultaneously.

### **Initialize a Vuser group**

If David wants to initialize all the Vusers in **Script\_C** simultaneously, he selects the script in the Scenario Groups pane and clicks the Initialize Vusers button  on the Controller toolbar. All Vusers that are still in the **Down** state are immediately initialized (in this case, only five). Their status changes from **Down** to **Pending** to **Initializing** to **Ready**. They then run according to their defined schedules.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	10	0	0	5	15	0	0	0	0	0	0	0
Script_A	5				5							
Script_B	5				5							
Script_C				5	5							

**Note:** Only Vusers that are in the **Down** state can be initialized. Vusers that have been initialized already are unaffected.

### **Run a Vuser group**

If David wants to run all the Vusers in **Script\_C** simultaneously, he selects the script in the Scenario Groups pane and clicks the **Run Vusers** button  on the Controller toolbar. All Vusers in the group that have not yet started running move to the **Run** state and begin executing their scripts.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	10	0	0	0	20	0	0	0	0	0	0	0
Script_A	5				5							
Script_B	5				5							
Script_C					10							

## Stop a Vuser Group

If David wants to stop all the Vusers in **Script\_C** from running, he has two options:

- **To stop them immediately**

He selects the script in the Scenario Groups pane and clicks the **Stop Vusers** button  on the Controller toolbar. All Vusers that have been initialized, or are already running, stop executing their scripts immediately and move directly to the **Stopped** state.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	0	0	0	0	10	0	0	0	0	2	0	18
Script_A					5					1		4
Script_B					5					1		4
Script_C												10

- **To stop them gradually**

He selects the script in the Scenario Groups pane and clicks the **Gradual Stop** button  on the Controller toolbar. All Vusers that have been initialized, or are already running, move to the **Gradual Exiting** state and then exit the scenario gradually as per their defined schedules.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	0	0	0	0	10	0	0	0	0	8	0	12
Script_A					5					1		4
Script_B					5					1		4
Script_C										6		4

**Note:** The group can only be stopped gradually if **Wait for the current iteration to end before exiting** or **Wait for the current action to end before exiting** have been selected in the Run-Time Setting tab of the Options dialog box. For more information, see "[Options > Run-Time Settings Tab](#)" on page 1182.

## Control Vusers During a Scenario Run - Use-Case Scenario

This use-case scenario describes how to override defined schedules and manually control the behavior, addition, and stopping of Vusers during a scenario run.

**Note:** For a task related to this scenario, see "[How to Run a Scenario](#)" on page 1191.

David Smith is a load tester at NewSoft Company, currently using LoadRunner to test a new product in preparation for its upcoming release.

His load test contains three Vuser groups, **Script\_A**, **Script\_B**, and **Script\_C**. Each group has been assigned **ten** Vusers and been given the same schedule definitions, that is, to start **two** Vusers every **ten** seconds, and to stop **two** Vusers every **ten** seconds.

If David were to leave these schedules as defined, the start and stop actions in the scenario groups pane would look as follows:

### Start

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	15	0	0	0	15	0	0	0	0	0	0	0
Script_A	5				5							
Script_B	5				5							
Script_C	5				5							

### Stop

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	0	0	0	0	15	0	0	0	0	3	0	12
Script_A					5					1		4
Script_B					5					1		4
Script_C					5					1		4

The following table shows the options available to David should he wish to override these defined schedules and manually manipulate the way the Vusers start or stop:

**Note:** All the following use-case scenario options refer back to the scenario explained above.

Control Vusers Option	Use-Case Scenario
Manipulate an entire Vuser group. <b>Example:</b> Run or stop all the Vusers in a group simultaneously.	" <a href="#">Initialize, Run, or Stop Vuser Groups - Use-Case Scenario</a> " on page 1193
Run/Stop individual Vusers, or add new Vusers. <b>Example 1:</b> Run/Stop a single Vuser currently in the down/run state. <b>Example 2:</b> (Vuser Group mode) Add a specified number of Vusers to a group without initializing or running them.	" <a href="#">Run/Stop Individual Vusers, or Add New Vusers - Use-Case Scenario</a> " on the next page
Initialize/Run/Stop any number of Vusers within a group.	" <a href="#">Initialize/Run Additional Vusers or Stop Running Vusers - Use-Case Scenario</a> " on page 1199

## Run/Stop Individual Vusers, or Add New Vusers - Use-Case Scenario


This use-case scenario describes how David can manipulate the behavior of individual Vusers during the scenario run, irrespective of their defined schedules. The examples will show how he can run or stop individual Vusers, as well as how he can add new Vusers to the scenario.

**Note:** The examples presented in this section demonstrate options in the Vusers dialog box. Not all information relevant for working with this dialog box necessarily appears here. For full information about working with the Vusers dialog box, see "["Vusers Dialog Box" on page 1072](#)".

### Run an individual Vuser

If David wants to immediately run an additional Vuser from **Script\_A**, in the Run tab, he clicks **Vusers** to open the Vusers dialog box.

By selecting **script\_a**, and **All Vusers** in the filter options at the top of the dialog box, the table displays a list of all the Vusers in **Script\_A**, and indicates that five are currently running, and that five are still down.



David then selects Vuser number 6 (or any Vuser in the **Down** state that he wishes to run), and clicks **Run**.


That Vuser is immediately initialized and moved to the **Run** state.

Group Name	Down	Pending	Init	Ready	Run	Rende
3	14	0	0	0	16	0
Script_A	4				6	
Script_B	5				5	
Script_C	5				5	

## Stop an individual Vuser

If David wants to stop one of the running Vusers in **Script\_A**, in the Run tab, he clicks **Vusers** to open the Vusers dialog box.

By selecting **script\_a**, and **All Vusers** in the filter options at the top of the dialog box, the table displays a list of all the Vusers in **Script\_A**, and indicates that five are currently running, and that five are still down.



He then selects Vuser number 1 (or any running Vuser that he wishes to stop), and then selects one of the stopping options:

- **Stop the Vuser gradually.** David clicks **Gradual Stop**, and the Vuser immediately moves from the **Run** state to the **Gradual Exiting** state, where it completes its current iteration or action before stopping.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	15	0	0	0	14	0	0	0	0	1	0	0
Script_A	5				4					1		
Script_B	5				5							
Script_C	5				5							


- **Stop the Vuser immediately.** David clicks **Stop**, and the Vuser immediately stops running and moves to the **Stopped** state.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	15	0	0	0	14	0	0	0	0	0	0	1
Script_A	5				4							1
Script_B	5				5							
Script_C	5				5							

## Add new Vusers (Vuser Group mode only)

If David is working in Vuser Group mode, he can add new Vusers to a group without initializing them, as follows:

In the Run tab, he clicks **Vusers** to open the Vusers dialog box, then he clicks **Add Vusers** to open the Add Vusers dialog box.



He then enters the following information (as shown in the image above):

- **Group Name.** script\_a
- **Quantity to add.** 5
- **Load Generator Name.** localhost (or any load generator on which the group is running Vusers).
- **Select Script.** Script\_A

These settings instruct LoadRunner to add five Vusers to **Script\_A**, and that the additional Vusers should run **Script\_A** when they run.

**Note:** For full information on how to work with the Add Vusers dialog box, see "["Add Vusers Dialog Box" on page 1053.](#)

He clicks **OK**. Five Vusers are added to **Script\_A** in the down state, from where they run according to the group's defined schedules.

Group Name	Down	Pending	Init	Ready	Run	Rende
3	16	0	2	0	12	0
Script_A	10				5	
Script_B	5				5	
Script_C	5				5	

## Initialize/Run Additional Vusers or Stop Running Vusers - Use-Case Scenario

This use-case scenario describes how David can manipulate the behavior of Vusers during a scenario run, irrespective of their defined schedules. The examples will show how he can initialize or run specified numbers of additional Vusers, or stop specified numbers of running Vusers.

**Note:** The examples presented in this section demonstrate options in the **Run/Stop Vusers** dialog box. Not all information relevant for working with this dialog box necessarily appears here. For full information about working with the **Run/Stop Vusers** dialog box, see "["Run/Stop Vusers Dialog Box" on page 1210.](#)

### Initialize/Run additional Vusers in Vuser group mode


The following procedure shows how David can initialize and run additional Vusers when he is working in Vuser Group mode:

**Note:** The options to initialize or run additional Vusers can be done as two separate actions, with no connection to each other. They are being shown here together as a single workflow for demonstrative purposes only.

#### 1. Initialize additional Vusers

If he wants to initialize **ten** Vusers in **Script\_A** immediately, and not wait for them to initialize as per their defined schedules, in the Run tab, he clicks **Run/Stop Vusers** to open the Run/Stop Vusers dialog box.

In the dialog box, he makes sure that only the check box by **script\_a** is selected, and he enters **10** in the **#** (number) column.




To initialize these Vusers, he clicks **Initialize**. Ten Vusers are immediately initialized and move to the **Ready** state. From there, they run according to their defined schedules.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	10	0	0	10	15	0	0	0	0	0	0	0
Script_A				10	5							
Script_B	5				5							
Script_C	5				5							

**Note:** The additional initialized Vusers are taken from the Vusers that are in the **Down** state. If David initializes a greater number of Vusers than there are in the **Down** state, then all of them will be initialized. In the example above, there were five Vusers in the **Down** state. All of them have been initialized, while an additional five have been created.

## 2. Run additional Vusers

If David then wants to run five additional Vusers in **Script\_A** immediately, and not wait for them to run as per their defined schedules, in the Run/Stop Vusers dialog box, he makes sure that only the check box by **script\_a** is selected, and he enters **5** in the **#** (number) column.



He then has the following two options for how to run these additional Vusers:

- **Run initialized Vusers.** He can run five Vusers from those he initialized in the previous step. To do this, he clicks the arrow on the **Run** button and selects **Run Initialized**. Five Vusers immediately move from the **Ready** state to the **Run** State.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stop
3	10	0	0	5	20	0	0	0	0	0	0	0
Script_A				5	10							
Script_B	5				5							
Script_C	5				5							

- **Run new Vusers.** He can create and run five new Vusers, with no effect on those he initialized in the previous step. To do this, he clicks the arrow on the **Run** button and selects **Run New**. Five Vusers are immediately created and move directly to the **Run** state.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stop
3	10	0	0	10	20	0	0	0	0	0	0	0
Script_A				10	10							
Script_B	5				5							
Script_C	5				5							

**Note:** If there were still Vusers in the **Down** state, the new Vusers would be taken from them.

## Initialize/Run additional Vusers in Percentage mode

The following procedure shows how David can initialize and run additional Vusers when he is working in Percentage mode:

**Note:** The options to initialize or run additional Vusers can be done as two separate actions, with no connection to each other. They are being shown here together as a single workflow for demonstrative purposes only.

### 1. Initialize new Vusers

If he wants to initialize ten Vusers in **Script\_A** immediately, and not wait for them to initialize as per their defined schedules, in the Run tab, he clicks **Run/Stop Vusers** to open the Run/Stop Vusers dialog box.

In the dialog box, he makes sure that only the check box by **script\_a** is selected, and he enters **10** in the **Distribute X Vusers among all the scripts** box. It is also important that the percentage values for **Script\_B** and **Script\_C** are set to **0%**. See the note below for a detailed explanation why.

**Note:** When a check box is deselected, no Vusers are distributed to that script. However, the amount of Vusers that *would* have been assigned to it are not redistributed to the scripts that remain selected, unless you specify **0%** in the percentage column.


For example, in our use-case scenario, when David enters **10** in the **Distribute X Vusers among all the scripts** box, LoadRunner automatically distributes these Vusers as equally as possible among the available scripts, that is:

- **script\_a.** 4 Vusers
- **script\_b.** 3 Vusers
- **script\_c.** 3 Vusers

However, should David wish to distribute all **10** Vusers to **script\_a**, it is not sufficient to simply deselect **script\_b** and **script\_c**. This only ensures that no Vusers are added to these scripts, but it *does not* change the original Vuser distribution.

In other words, should David complete the step now, the four Vusers that are assigned to **script\_a** will be added, while the three each assigned to **script\_b** and **script\_c** will not, though they will still appear under the # (number) column. To distribute these six Vusers to **script\_a** instead, David must first change the % (percentage) columns for these scripts to **0%**.


He then clicks **Initialize**. Ten Vusers are immediately initialized and move to the **Ready** state. From there, they run according to their defined Scheduler settings.



**Note:** The additional initialized Vusers are taken from the Vusers that are in the **Down** state. If you initialize a greater number of Vusers than there are in the **Down** state, then all of them will be initialized. In the example above, there were five Vusers in the **Down** state. All of them have been initialized, while an additional five have been created.

- Run additional Vusers

If David then wants to run five additional Vusers in **Script\_A** immediately, and not wait for them to run as per their defined schedules, in the Run/Stop Vusers dialog box, he makes sure that only the check box by **script\_a** is selected, and he enters **5** in the **Distribute X Vusers among all the scripts** box at the top of the dialog box. It is also important that the percentage values for **Script\_B** and **Script\_C** are set to **0%**. See the note in the step above for a detailed explanation why.



He then has the following two options for how to actually run these additional Vusers:

- **Run initialized Vusers.** He can run five Vusers from those he initialized in the previous step. To do this, he clicks the arrow on the **Run** button and selects **Run Initialized**. Five Vusers immediately move from the **Ready** state to the **Run State**.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	10	0	0	5	20	0	0	0	0	0	0	0
Script_A				5	10							
Script_B	5				5							
Script_C	5				5							

- **Run new Vusers.** He can create and run five new Vusers, with no effect on those he initialized in the previous step. To do this, he clicks the arrow on the **Run** button and selects **Run New**. Five Vusers are immediately created and move directly to the **Run** state.


Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	10	0	0	10	20	0	0	0	0	0	0	0
Script_A				10	10							
Script_B	5				5							
Script_C	5				5							

**Note:** If there were still Vusers in the **Down** state, the new Vusers would be taken from them.

## Stop running Vusers in Vuser group mode

If David wants to stop **three** of the **five** running Vusers in **Script\_A**, and not wait for them to stop as per their defined schedules, in the Run tab, he clicks **Run/Stop Vusers** to open the Run/Stop Vusers dialog box.

In the dialog box, he makes sure that only the check box by **script\_a** is selected, and he enters **3** in the **#** (number) column.




He then clicks **Stop**. Three of the running Vusers in **Script\_A** move from the **Run** state to the **Gradual Exiting** state.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	0	0	0	0	12	0	0	0	0	6	0	12
Script_A					2					4		4
Script_B					5					1		4
Script_C					5					1		4

## Stop running Vusers in Percentage mode

If David wants to stop **three** of the **five** running Vusers in **Script\_A**, and not wait for them to stop as per their defined schedules, in the Run tab, he clicks **Run/Stop Vusers** to open the Run/Stop Vusers dialog box.

In the dialog box, he makes sure that only the check box by **script\_a** is selected, and he enters **3** in the **Distribute X Vusers among all the scripts** box. It is also important that the percentage values for **Script\_B** and **Script\_C** are set to **0%**. See the note below for a detailed explanation why.



**Note:** When a check box is deselected, no Vusers are distributed to that script. However, the amount of Vusers that *would* have been assigned to it are not redistributed to the scripts that remain selected, unless you specify **0%** in the percentage column.

For example, in our use-case scenario, when David enters **3** in the **Distribute X Vusers among all the scripts** box, LoadRunner automatically distributes these Vusers as equally as possible among the available scripts, that is:

**script\_a.** 1Vuser  
**script\_b.** 1Vuser  
**script\_c.** 1Vuser

However, should David wish to distribute all **3** Vusers to **script\_a**, it is not sufficient to simply deselect **script\_b** and **script\_c**. This only ensures that no Vusers are added to these scripts, but it *does not* change the original Vuser distribution.

In other words, should David complete the step now, the single Vuser that is assigned to **script\_a** will be stopped, while the one each assigned to **script\_b** and **script\_c** will not, though they will still appear under the **#** (number) column. To distribute these two Vusers to **script\_a** instead, David must first change the **%** (percentage) columns for these scripts to **0%**.

He then clicks **Stop**. Three of the running Vusers in **Script\_A** move from the **Run** state to the **Gradual Exiting** state.

Group Name	Down	Pending	Init	Ready	Run	Rendez	Passed	Failed	Error	Gradual Exiting	Exiting	Stopped
3	0	0	0	0	12	0	0	0	0	6	0	12
Script_A					2					4		4
Script_B					5					1		4
Script_C					5					1		4

## Execution Notes Dialog Box

This page dialog box enables you to log comments while a scenario is running.

<b>To access</b>	Select <b>Scenario &gt; Execution Notes</b>
<b>Relevant tasks</b>	"How to Run a Scenario" on page 1191
<b>Important Information</b>	Only enabled while the scenario is running.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<note writing area>	Enter your notes in this area.

## Output Window

This window displays error, notification, warning, debug, and batch messages that are sent to the Controller by the Vusers and load generators during a scenario run.

<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• Run tab &gt; <b>Scenario Status</b> pane &gt; <b>Errors</b> &gt; </li><li>• Select <b>View &gt; Show Output</b></li></ul>
<b>Important information</b>	<ul style="list-style-type: none"><li>• LoadRunner clears the messages in the Output window at the start of each scenario execution. If you reset a scenario, messages remain in the Output window unless you instruct LoadRunner to delete messages from the window upon reset. For more information, see "Options &gt; Output Tab" on page 1180.</li><li>• The Summary tab is displayed by default when you open this window.</li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• "How to Run a Scenario" on page 1191</li><li>• "How to Configure Scenario Options" on page 1172</li></ul>

User interface elements are described below:

UI Element	Description
<b>Filtered Tab</b>	See "Filtered Tab" below
<b>Summary Tab</b>	See "Summary Tab" on page 1207

## Filtered Tab

This tab displays a drilled down view by message, Vuser, script, or load generator. For example, if you drill down on the Vuser column, the Filtered tab displays all the messages with the code you selected, grouped by the Vusers that sent the messages.

<b>To access</b>	<b>Output window &gt; Filtered tab.</b> Click the blue link on the column about which you wish to view more information.
<b>Important information</b>	The tab appears when you click on a blue link in the Summary tab.
<b>See also</b>	<a href="#">"Summary Tab" on the next page</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Previous/Next View.</b> Enables you to move between the various drill down levels.
Details	Displays the full text of the selected output message in the Detailed Message Text area at the bottom of the Output window.
	<b>Export the view.</b> Saves the output to a specified file.
Refresh	Refreshes the Filtered tab with new log information that arrived in the Output window updated in the Summary tab.
<Message icon>	Displays an icon indicating the type of message by which the current Output view is filtered.
<b>Active Filter</b>	Displays the category or categories by which the current Output view is filtered.
<b>Viewed By</b>	Displays the name of the column on which you selected to drill down. The following icons indicate the various message types: <ul style="list-style-type: none"> <li>•  Batch</li> <li>•  Debug</li> <li>•  Errors</li> <li>•  Notifications</li> <li>•  Warnings</li> </ul>
<b>Detailed Message Text</b>	Displays the full text of the selected output message when the <b>Details</b> button is selected.
<b>Message</b>	Displays all instances of the sample message text.



<b>Script</b>	The script on which the message was generated. If you click the blue link, VuGen opens displaying the script.
<b>Action</b>	The action in the script where the message was generated. If you click the blue link, VuGen opens the script to the relevant action.
<b>Line #</b>	The line in the script where the message was generated. If you click the blue link, VuGen opens the script and highlights the relevant line.
<b># Lines</b>	The total number of lines in the script where the Vuser failed.
<b>Time</b>	The time the message was generated.
<b>Iteration</b>	The iteration during which the message was generated.
<b>Vuser</b>	The Vuser that generated the message.
<b>Generator</b>	The load generator on which the message was generated. If you click the blue link, the Load Generator dialog box opens.
<b># Messages</b>	The number of messages generated by a specific Vuser.
<b># Diff Texts</b>	

## Summary Tab

This tab displays summary information about the messages sent during a scenario run.

<b>To access</b>	Output window > <b>Summary</b> tab
<b>Important information</b>	You can drill down further on any information displayed in blue.
<b>See also</b>	" <a href="#">Filtered Tab</a> " on page 1205

User interface elements are described below:

UI Element	Description
 Details	Displays the full text of the selected output message in the Detailed Message Text area at the bottom of the Output window.
	<b>Remove all messages.</b> Clears all log information from the Output window.
	<b>Export the view.</b> Saves the output to a specified file.
 Freeze	<ul style="list-style-type: none"> <li><b>Freeze.</b> Stops updating the Output window with messages.</li> </ul>
 Resume	<ul style="list-style-type: none"> <li><b>Resume.</b> Resumes updating the Output window with messages. The newly updated log information is displayed in a red frame.</li> </ul>

<b>Detailed Message Text</b>	Displays the full text of the selected output message when you click the <b>Details</b> button.
<b>Generators</b>	Displays the number of load generators that generated messages with the specified message code.
<b>Help</b>	Displays an icon if there is a link to troubleshooting for the message.
<b>Message Code</b>	Displays the code assigned to all similar messages. The number in parentheses indicates the number of different codes displayed in the Output window.
<b>Sample Message Text</b>	Displays an example of the text of a message with the specified code.
<b>Scripts</b>	Displays the number of scripts whose execution generated messages with the specified code.
<b>Total Messages</b>	Displays the total number of sent messages with the specified code.
<b>Type</b>	The type of message being displayed. The following icons indicate the various message types. For more information about each type, see <b>Type of Message</b> below: <ul style="list-style-type: none"><li>•  Batch</li><li>•  Debug</li><li>•  Errors</li><li>•  Notifications</li><li>•  Warnings</li></ul>

Type of Message	<p>Filters the output messages to display only certain message types. Select one of the following filters:</p> <ul style="list-style-type: none"><li><b>All messages.</b> Displays all message types.</li><li><b>Batch.</b> Sent instead of message boxes appearing in the Controller, if you are using automation.</li><li><b>Debug.</b> Sent only if the debugging feature is enabled in the Controller. (Expert mode: <b>Tools &gt; Options &gt; Debug Information</b>). For more information, see "<a href="#">Options &gt; Debug Information Tab</a>" on page 1176.</li><li><b>Errors.</b> Usually indicate that the script failed.</li><li><b>Notifications.</b> Provides run-time information, such as message sent using <code>lr_output_message</code>.</li><li><b>Warnings.</b> Indicates that the Vuser encountered a problem, but the scenario continued to run.</li></ul>
Vusers	Displays the number of Vusers that generated messages with the specified code.



## Run Tab

The Run tab enables you to run and monitor scenarios.

To access	Run tab
Relevant tasks	<ul style="list-style-type: none"><li><a href="#">"How to Run a Scenario" on page 1191</a></li><li><a href="#">"Control Vusers During a Scenario Run - Use-Case Scenario" on page 1194</a></li></ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 Start Scenario	<p>Instructs the Controller to initialize the Vusers and distribute them to their designated load generators, where they begin running their Vuser scripts.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"><li>The Controller begins running the scenario according to the start time defined in the scenario schedule.</li><li>We do not recommend changing the Time/Date and Time Zone settings on the Controller and load generators during the load test run.</li></ul>

 Stop	Terminates the scenario. The behavior depends on your selection in the <b>Tools &gt; Options &gt; Run-Time Settings</b> tab:
 Stop Now	<ul style="list-style-type: none"> <li>If you selected <b>Stop immediately</b>, all Vusers in the scenario move to the <b>Exiting</b> status.</li> <li>If you selected <b>Wait for the current iteration to end before exiting</b>, or <b>Wait for the current action to end before exiting</b>, the button text changes to <b>Stop Now</b> and the Vusers status changes to <b>Gradual Exiting</b>. To stop the Vusers immediately, click <b>Stop Now</b>.</li> </ul> <p>For more information about the Run-Time Settings options, see "<a href="#">Options &gt; Run-Time Settings Tab</a>" on page 1182.</p>
 Reset	Resets all Vuser groups to the <b>Down</b> status.
	Opens the Vusers dialog box, where you can view the status of each of the Vusers in a Vuser group.
 Run/Stop Vusers...	Opens the Run/Stop Vusers dialog box, where you can activate additional Vusers.
 Pause Scheduler	Pauses or resumes the scenario schedule.
 Resume Scheduler	
<Graph Legend>	Displays statistics for the selected graph. For more information, see " <a href="#">Online Monitor Graphs</a> " on page 1156.
<Graph Viewing Pane>	Displays the graphs that are listed in the <b>Available Graphs</b> pane. For more information, see " <a href="#">Online Monitor Graphs</a> " on page 1156. <b>Default:</b> Displays four graphs
Available Graphs	Displays the available online monitor graphs. For more information, see " <a href="#">Online Monitor Graphs</a> " on page 1156.
Scenario Groups pane	Displays each Vuser group and its current status. For more information, see " <a href="#">Scenario Groups Pane</a> " on page 1213.
Scenario Status pane	Displays a synopsis of the running scenario. For more information, see " <a href="#">Scenario Status Pane</a> " on page 1215.

## Run/Stop Vusers Dialog Box

This dialog box enables you to manually control the addition of new Vusers to a running scenario, as well as to stop running Vusers.

<b>To access</b>	Run tab > Scenario Groups pane > 
<b>Important information</b>	<ul style="list-style-type: none"> <li>The dialog box differs depending on which mode you are working in.</li> <li> <ul style="list-style-type: none"> <li><b>Vuser group mode.</b> You specify the number of new Vusers to be added to each Vuser group, as well as the load generators on which these additional Vusers will run.</li> <li><b>Percentage mode.</b> You specify the percentage of Vusers to be added to each script, as well as the load generators on which these additional Vusers will run.</li> </ul> </li> <li>When you add Vusers to a running scenario or Vuser group, the current scheduler settings are automatically applied to all new Vusers. For example, if the scenario or Vuser group has a set duration of five minutes, all Vusers that are subsequently added run only for the remaining part of that time period.</li> </ul> <p>Vusers that are added to a scenario or Vuser group which has finished running, are not affected by schedule settings and run according to the scenario run-time settings.</p>
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li><a href="#">"How to Run a Scenario" on page 1191</a></li> <li><a href="#">"Control Vusers During a Scenario Run - Use-Case Scenario" on page 1194</a></li> </ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 Init	Distributes the added Vusers to their designated load generators so that they are ready to execute their scripts. The Controller first initializes the Vusers in your scenario that have not yet run and then adds additional Vusers, as required, to reach the defined quantity.
 Run  Run Initialized Run New	<ul style="list-style-type: none"> <li><b>Run Initialized.</b> Runs the Vusers in the scenario that have already been initialized.</li> <li><b>Note:</b> You cannot run more Vusers than are currently initialized using this option.</li> <li><b>Run New.</b> Runs the number of Vusers you specified. The Controller first runs the Vusers in your scenario that have not yet been run and then adds additional Vusers, as required, to reach the defined quantity.</li> </ul>
 Stop	Stops the Vusers that are running. The Controller stops the Vusers according to the settings you defined in the Run-Time Settings tab. For more information, see <a href="#">"Options &gt; Run-Time Settings Tab" on page 1182</a> .

, continued

<b>&lt;check box&gt;</b>	<p>Selects the Vuser groups/scripts you add Vusers to.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>• To disable a Vuser group/script, clear the check box to the left of the group/script name. A group/script automatically appear disabled if it is disabled in the Design view.</li> <li>• When you disable a Vuser group (Vuser Group mode), no Vusers are added to the group.</li> <li>• When you disable a script (Percentage mode), no Vusers are distributed to the script, and the unused percentage of the Vusers are not distributed among the remaining scripts, unless you define a zero percent value for the disabled script.</li> </ul> <p><b>Example:</b> If you have three scripts, <b>A</b>, <b>B</b>, and <b>C</b>, and you enter <b>10</b> in the <b>Distribute X Vusers among all the scripts</b> box, LoadRunner automatically distributes these Vusers as equally as possible among the scripts, that is:</p> <ul style="list-style-type: none"> <li>▪ <b>A.</b> 4 Vusers</li> <li>▪ <b>B.</b> 3 Vusers</li> <li>▪ <b>C.</b> 3 Vusers</li> </ul> <p>However, if you want LoadRunner to distribute <i>all</i> 10 Vusers to <b>A</b>, it is not sufficient to simply deselect <b>B</b> and <b>C</b>. This only ensures that no Vusers are added to these scripts, but it <i>does not</i> change the original Vuser distribution. In other words, if you were to finish the step now, the four Vusers that are assigned to <b>A</b> <i>would be</i> added to the script, while the three each assigned to <b>B</b> and <b>C</b> <i>would not</i>, though they would still appear under the <b>#</b> (number) column. To distribute these <b>six</b> Vusers to <b>A</b> instead, you must first change the <b>%</b> (percentage) columns <b>B</b> and <b>C</b> to <b>0%</b>.</p>
<b>%</b> (Percentage mode)	Enter the percentage of Vusers to be distributed to each Vuser script.
<b>#</b>	Indicates the number of Vusers distributed to each script.
<b>Distribute x Vusers among the checked scripts</b> (Percentage mode)	Enter the number of Vusers to be distributed. The Vusers will be distributed according to the values you entered in the percentage (%) column.

, continued

<b>Load Generators</b>	The load generators assigned to the Vuser group/script. If you select multiple load generators for a group/script, the Vusers assigned to the Vuser group/script are distributed evenly among the load generators. <b>Default value (in Percentage mode):</b> All Load Generators <b>Note:</b> To add a load generator to the list, select <b>Add</b> from the list. For more details see " <a href="#">Add New Load Generator/Load Generator Information Dialog Box</a> " on page 1085.
------------------------	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

## Scenario Groups Pane

This pane enables you to monitor the actions of all the Vusers and Vuser groups in the scenario.

<b>To access</b>	Run tab
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• "<a href="#">How to Run a Scenario</a>" on page 1191</li><li>• "<a href="#">Control Vusers During a Scenario Run - Use-Case Scenario</a>" on page 1194</li></ul>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
------------	-------------

, continued

<b>&lt;Right-click menu&gt;</b>	<p>Additional actions available only via the right-click menu:</p> <ul style="list-style-type: none"> <li>• <b>Reset IDs.</b> Resets the IDs of the Vusers in the group.</li> <li>• <b>Run Vusers Until Complete.</b> Runs the selected Vusers until complete. If you run Vusers in the <b>Down</b> or <b>Error</b> state, the Controller initializes and then runs the Vusers.</li> <li>• <b>Run One Vuser Until Complete.</b> Instructs the Controller to run a randomly selected Vuser in the Vuser group, until it completes running. The Vuser Log opens, displaying run-time information about the Vuser. For more information, see "<a href="#">"Vuser Script Log" on page 1216</a>".</li> <li>• <b>Pause Vusers.</b> Temporarily pauses running the Vusers group. The status of the Vuser group changes from <b>Running</b> to <b>Paused</b>. Note that pausing a Vuser group affects its transaction response time.</li> <li>• <b>Enable.</b> Enables the Vuser group to participate in the scenario.</li> <li>• <b>Disable.</b> Disables the Vuser group so that it no longer participates in the scenario.</li> <li>• <b>Show Vuser Log.</b> Opens a script log containing run-time information for each Vuser in the group. The Vuser script log is refreshed, by default, every 1000 milliseconds.</li> <li>• <b>Hide Vuser Log.</b> Closes the Vuser script logs.</li> <li>• <b>Sort By Name.</b> Sorts the groups alphabetically, by name.</li> </ul>
<b>Done/Failed</b>	The number of Vusers that have finished running and the script failed.
<b>Done/Passed</b>	The number of Vusers that have finished running and the script passed.
<b>Down</b>	The number of Vusers that have stopped running.
<b>Error</b>	The number of Vusers that encountered problems. Check the Status field on the Vuser dialog box or the output window for a complete explanation of the error.
<b>Exiting</b>	The number of Vusers that have finished running or have been stopped, and are now exiting.
<b>Gradual Exiting</b>	The number of Vusers that are completing their iterations or actions before exiting (as defined in <b>Tools &gt; Options &gt; Run-Time Settings</b> ).
<b>Initializing</b>	The number of Vusers that are being initialized on the remote machine.
<b>Pending</b>	The number of Vusers that are ready to be initialized and are waiting for an available load generator, or are transferring files to the load generator.

, continued

<b>Ready</b>	The number of Vusers that have already performed the init section of the script and are ready to run.
<b>Rendezvous</b>	The number of Vusers that have arrived at the rendezvous and are waiting to be released by the Controller.
<b>Running</b>	The number of Vusers that are running, and the Vuser script is being executed on a load generator.
<b>Stopped</b>	The Vuser stopped when the Stop command was invoked.

## Scenario Status Pane

This pane displays a synopsis of the running scenario.

<b>To access:</b>	<b>Run tab</b>
<b>Important Information</b>	To detach the Scenario Status pane from the Run tab, click the detach pane  button in the upper right corner.
<b>Relevant tasks</b>	<a href="#">"How to Run a Scenario" on page 1191</a>

User interface elements are described below:

UI Element	Description
<b>Elapsed Time</b>	Indicates how much time has elapsed since the scenario started running.
<b>Errors</b>	Indicates the number of Vusers with errors. To display the errors, click the <b>Show Snapshot</b>  button to display the Output Window. For more information, see <a href="#">"Output Window" on page 1205</a> .
<b>Hits/Second</b>	Indicates how many hits (HTTP requests) there have been to the Web site being tested per second that each Vuser has been running.
<b>Passed/Failed Transactions</b>	Indicates how many transactions have been executed successfully or unsuccessfully. For more information, see <a href="#">"Transactions Dialog Box" below</a> .
<b>RunningVusers</b>	Indicates the number of Vusers that are currently running.
<b>Scenario Status</b>	Indicates whether the scenario is <b>Running</b> or <b>Down</b> .

## Transactions Dialog Box

This dialog box indicates how many transactions have been executed successfully or unsuccessfully.

To access	Run tab > <b>Scenario Status</b> pane. Click the Show Snapshot  button by Passed/Failed Transactions.
Important information	VuGen automatically defines each <b>Init</b> , <b>Action</b> , and <b>End</b> unit as a transaction. In addition, you can insert a static transaction in your script using the Start Transaction and End Transaction functions. For details, see " <a href="#">How to Insert Transactions</a> " on page 398.
Relevant tasks	<a href="#">"How to Run a Scenario" on page 1191</a>
See also	<a href="#">"Scenario Status Pane" on the previous page</a>

User interface elements are described below:

UI Element	Description
Failed	The number of times the transaction failed.
Name	The names of the individual transactions in a script.
Passed	The number of times the transaction passed.
Stopped	The number of times the transaction stopped.
TPS	The number of times per second the transaction has run.

## Vuser Script Log

This page enables you to view run-time information about each running Vuser.

To access	Manual scenario > Run tab > <b>Scenario Groups</b> pane > <b>Vusers</b>  . In the Vusers dialog box select the Vuser whose log you want to view and click <b>Show Vuser Log</b>  .
Important information	<ul style="list-style-type: none"><li>If you disabled the logging feature in the Run-Time Settings <b>Log</b> node, the Vuser script log will contain output only if your script contains the <b>lr_output_message</b> or <b>lr_message</b> function.</li><li>If you selected the <b>Send messages only when an error occurs</b> option in the <b>Log</b> node, the Vuser script log will contain output only if there are script errors.</li></ul>
Relevant tasks	<a href="#">"How to Run a Scenario" on page 1191</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description

	<b>Show Text/Tree View.</b> Displays the run-time information in text/tree format. To revert to the previous view, click the button again.
	<b>Display.</b> Displays a snapshot of the Web page where an error occurred, when the error is highlighted in the Vuser log. <b>Notes:</b> <ul style="list-style-type: none"> <li>To view a snapshot of the Web page where an error occurred, you must select the <b>Activate snapshot on error</b> option in the <b>General</b> node of the Run-Time Settings dialog box before running the scenario.</li> <li>Snapshots on errors is supported for TruClient.</li> </ul>
	<b>Find Text.</b> Enables you to search for text in the Vuser log.
	<b>Expand/Collapse Node.</b> Expands the node so that you can view additional run-time information details about the Vuser. To revert to the collapsed tree view, click the button again.
<b>&lt;message icons&gt;</b>	The following icons may appear in the script log: <ul style="list-style-type: none"> <li> <b>Action.</b> Displays the name and description of an action.</li> <li> <b>End iteration.</b> Indicates the end of an iteration.</li> <li> <b>Errors.</b> Indicates that the Vuser encountered a problem, but test execution continued. Displays the error code and a description of the error.</li> <li> <b>Notifications.</b> Provides action information.</li> <li> <b>Start/End Transaction.</b> Indicates the start or end of a transaction.</li> <li> <b>Start iteration.</b> Indicates the start of an iteration.</li> <li> <b>Start User Script.</b> Indicates the start of the Vuser script.</li> </ul>
<b>&lt;Right-click options&gt;</b>	<ul style="list-style-type: none"> <li><b>Copy.</b> Enables you to copy selected text from the Vuser log.</li> <li><b>Copy path from status bar.</b> Enables you to copy the path of the Vuser log.</li> </ul>
<b>Refresh (every 1000 milliseconds)</b>	When selected, instructs LoadRunner to refresh the run-time information displayed every 1000 milliseconds. <b>Note:</b> For information on how to change the default refresh settings, see " <a href="#">Options &gt; Output Tab</a> " on page 1180.

## Rendezvous Points

## Rendezvous Points Overview

During a scenario run, you can instruct multiple Vusers to perform tasks simultaneously by using **rendezvous points**. A rendezvous point creates intense user load on the server and enables LoadRunner to measure server performance under load.

Suppose you want to measure how a Web-based banking system performs when ten Vusers simultaneously check account information. To emulate the required user load on the server, you instruct all the Vusers to check account information at exactly the same time.

You ensure that multiple Vusers act simultaneously by creating a rendezvous point. When a Vuser arrives at the rendezvous point, it is held there by the Controller. You then set a **rendezvous policy** according to which the Controller releases the Vusers from the rendezvous point either when the required number of Vusers arrives, or when a specified amount of time has passed.

You define rendezvous points in the Vuser script. For information about inserting rendezvous points into Vuser scripts, see "["Rendezvous Points" on page 400](#)".

Using the Controller, you can influence the level of server load by selecting:

- Which of the rendezvous points will be active during the scenario
- How many Vusers will take part in each rendezvous

For example, to test a bank server, you could create a scenario that contains two rendezvous points. The first rendezvous ensures that 1000 Vusers simultaneously deposit cash. The second rendezvous ensures that another 1000 Vusers simultaneously withdraw cash. If you want to measure how the server performs when only 500 Vusers deposit cash, you can deactivate the **withdraw** rendezvous, and instruct 500 Vusers to participate in the **deposit** rendezvous only.

## How to Set Up a Rendezvous in a Scenario

This task describes set up rendezvous points and policies in a scenario.

### 1. Prerequisites

To set up a rendezvous in the scenario, your scenario must include Vuser scripts that have rendezvous points inserted in them. For information about inserting rendezvous points into Vuser scripts, see "["Rendezvous Points" on page 400](#)".

When you add a Vuser group or script to the scenario, LoadRunner scans the included scripts for the names of the rendezvous points and adds them to the list of rendezvous points. You can the list of all the rendezvous points in your scenario by selecting **Scenario > Rendezvous**.

**Note:** In goal-oriented scenarios, a script's rendezvous points are disabled.

### 2. Set the level of emulated user load

Select the rendezvous points to take part in the scenario, and the number of Vusers to participate in each rendezvous. For user interface details, see "[Rendezvous Information Dialog Box](#)" below.

You can temporarily disable a rendezvous and exclude it from the scenario. You can disable a rendezvous point for all Vusers in a scenario, or you can temporarily disable specific Vusers from participating in the rendezvous.

By disabling and enabling a rendezvous, you influence the level of server load.

### 3. Set the attributes for the rendezvous policy - Optional

In the Rendezvous Information dialog box, for each rendezvous:

- a. Select the rendezvous, and click the **Policy** button.
- b. In the Policy dialog box, set the **policy** attributes as follows:
  - **Release.** How many Vusers will be released from a rendezvous at a time.
  - **Timeout.** How long the Controller waits before releasing Vusers from a rendezvous.

For user interface details, see "[Rendezvous Information Dialog Box](#)" below.



## Rendezvous Information Dialog Box

This dialog box enables you to view and modify the attributes of each rendezvous point in the scenario. It displays general information about the rendezvous point: which script is associated with the rendezvous, and release history.

To access	Manual scenario > <b>Design</b> tab > <b>Scenario</b> > <b>Rendezvous</b>
Important information	Available only if one of the Vuser scripts participating in the scenario contains a rendezvous point.
Relevant tasks	<a href="#">"How to Set Up a Rendezvous in a Scenario" on the previous page</a>

User interface elements are described below:

UI Element	Description
 Disable Rendezvous	Disables the rendezvous, excluding it from the scenario, thereby influencing the level of server load.
 Enable Rendezvous	Enables a disabled rendezvous point.

 Policy...	<p>Opens the Policy dialog box, where you can set the number Vusers to be released from a rendezvous at a time, as well as the amount of time the Controller waits before releasing Vusers from a rendezvous.</p> <ul style="list-style-type: none"><li><b>Release when X% of all Vusers arrive at the rendezvous.</b> Releases the Vusers only when the specified percentage of all Vusers arrives at the rendezvous point.<p>This option interferes with the scheduling of your scenario. If you select this option, your scenario will not run as scheduled.</p></li><li><b>Release when X% of all running Vusers arrive at the rendezvous.</b> Releases the Vusers only when the specified percentage of all Vusers running in the scenario arrives at the rendezvous point.</li><li><b>Release when X Vusers arrive at the rendezvous.</b> Releases the Vusers only when the specified number arrives at the rendezvous point.</li><li><b>Timeout between Vusers.</b> The timeout value (in seconds). After each Vuser arrives at the rendezvous point, LoadRunner waits up to the maximum timeout period specified for the next Vuser to arrive. If the next Vuser does not arrive within the timeout period, the Controller releases all the Vusers from the rendezvous. Each time a new Vuser arrives, the timer is reset to zero. You set a timeout for each rendezvous point.</li></ul> <p><b>Default value:</b> 30 seconds</p>
 Disable VUser	Disables a Vuser from taking part in the rendezvous.
 Enable VUser	Enables a Vuser to take part in the rendezvous.
 Reset	Resets the Status Information, removing the information currently displayed.
 Release	While a scenario is running, enables you to manually release Vusers from a rendezvous before the Controller releases them. Use this option if you want the scenario to continue running even though all the Vusers did not reach the rendezvous.
Rendezvous	The names of the rendezvous points in the scenario.
Scripts	The Vuser scripts that are associated with the rendezvous points.

<b>Status Information</b>	During and after a scenario, displays: <ul style="list-style-type: none"><li><b>Current Status.</b> The number of Vusers that arrived at the rendezvous point out of the total number of Vusers assigned to the rendezvous.</li><li><b>Time.</b> The time at which the Vusers at the rendezvous point were released.</li><li><b>Reason.</b> The reason the Vusers at the rendezvous point were released. The possible reasons are <b>Timeout</b> or <b>Arrived</b>.</li></ul>
<b>Vusers</b>	The Vusers associated with the rendezvous points.

## After the Scenario Run

### ***Post Scenario Run Procedures - Overview***

After the scenario runs you analyze the results using HP LoadRunner Analysis. If the run results are stored locally on each participating load generator, they need to be gathered into one location so that they can be processed for analysis. Diagnostics results on the mediators and servers must also be gathered. This process is known as **data collation**.

For details about collating run results and diagnostics data, see "["Collating Run Data" below](#)".

For details about analyzing the scenario run, see the *HP LoadRunner Analysis User Guide*.

### ***Collating Run Data***

When you run a scenario, by default all the run data is stored locally on each load generator. After scenario execution, the results must be collated—that is, the results from all of the load generators must be gathered and transferred to the results folder—before any analysis data can be generated.

In addition, data from the diagnostics servers or mediators must be collated as well.

You can set LoadRunner to collate the run data automatically, as soon as the run is complete. Alternatively, you can collate the run data manually after the run. This way, you can save and close a scenario and collate the data after reopening the scenario in the Controller.

The data that is collated include the result, diagnostics, and log files. After LoadRunner has successfully collated the data, these files are deleted from the load generators and diagnostics mediators from which they were gathered.

**Note:** In Expert mode, you can disable the collation of the log file collation (see "["How to Configure Scenario Options" on page 1172](#)").

For details on how to collate run data, see "["How to Collate Scenario Run Results" on the next page](#)".

## How to Collate Scenario Run Results

This task describes how to collate results after a scenario run.

### Note:

- Data collation includes result, diagnostics, and log files. If you are working in Expert mode, you can disable the collation of the log files. Before collating the results, select **Tools > Options > General tab > Do not collate log files**.
- You can set a command to run when collation is complete. Select **Tools > Options > Execution tab**, and enter the command in the **Post Collate Command** box.

### Collate results automatically

Select **Results > Auto Collate Results**.

### Collate results manually

Select **Results > Collate Results > Collate Results**.

### Stop the collation process

In the Collate Results dialog box, click **Stop**.

### Resume the collation process

If you stopped the collation process, to resume select **Results > Collate Results > Continue stopped collation**.

### If collation fails due to a lack of disk space

To re-collate, select **Results > Collate Results > Recollate**. LoadRunner attempts to collate the results again, without compressing the .eve file.

## Results Folder File Structure

Before you run a scenario, you specify where the run results should be stored. LoadRunner saves all the data it gathers during the run to the specified folder. A typical results folder has the following structure:

Address C:\Documents and Settings\ltron\Local Settings\Temp\res		
Name	Size	Type
log		File Folder
sum_data		File Folder
basic_script.cfg.bak	2 KB	BAK File
sap_c_and_s.cfg.bak	3 KB	BAK File
sap_c_and_s_1.cfg.bak	3 KB	BAK File
basic_script.cfg	2 KB	CFG File
sap_c_and_s.cfg	3 KB	CFG File
sap_c_and_s_1.cfg	3 KB	CFG File
offline.dat	0 KB	DAT File
_t_rep.eve	2 KB	EVE File
localhost_1.eve	18 KB	EVE File
localhost_1.map	2 KB	MAP File
output.mdb	468 KB	MDB File
res.lrr	1 KB	Mercury LoadRunne...
collate.txt	1 KB	Text Document
HostEmulatedLocation.txt	1 KB	Text Document
remote_results.txt	1 KB	Text Document
basic_script.usp	2 KB	USP File
sap_c_and_s.usp	3 KB	USP File
sap_c_and_s_1.usp	3 KB	USP File
SLAConfiguration.xml	1 KB	XML Document

The content of the results folder are described in the following table:

Folder/File	Description
<b>log folder</b>	Output information generated during replay for each Vuser
<b>sum_data folder</b>	Graph summary data (.dat) files.
<b>*_bd directories</b>	Diagnostics breakdown information.
<b>*.cfg files</b>	A listing of the script's run-time settings as defined in VuGen (think time, iterations, log, Web, and so on). The results folder contains a .cfg file for each script.
<b>*.def files</b>	Definition files for graphs that describe the online and other custom monitors.
<b>*.usp files</b>	Contain the script's run logic, including how the actions sections run. The results folder contains a .usp file for each script.
<b>_t_rep.eve</b>	Contains Vuser and rendezvous information.
<b>&lt;Controller&gt;.eve</b>	Contains information from the Controller host.
<b>&lt;Load_Generator&gt;.eve.gzl files</b>	Information from the load generators in the scenario. These files are zipped and saved to the results folder in .gzl format.

<b>&lt;Load_Generator&gt;.map</b>	Maps transactions and data points on the load generator to IDs.
<b>&lt;results_name&gt; folder</b>	The scenario run results.
<b>&lt;results_name&gt;.lrr</b>	Information about the scenario run, such as the name, duration, scripts included, and so on.
<b>collate.txt</b>	The file paths of the result files and collation status information.
<b>collateLog.txt</b>	The status (succeeded, failed) of result, diagnostics, and log file collation from each load generator.
<b>HostEmulatedLocation.txt</b>	Information about network virtualization such as the locations and mode (per group or load generator).
<b>offline.dat</b>	Sample monitor information.
<b>output.mdb</b>	The database created by the Controller. Stores all the output messages reported during the scenario run.
<b>remote_results.txt</b>	The file paths for the host event files
<b>SLAConfiguration.xml</b>	SLA definition information for the scenario.

When you generate analysis graphs and reports, the Analysis engine copies all of the scenario result files (**.eve** and **.lrr**) to a database. After the database is created, Analysis works directly with the database and does not use the result files.

## Collate Results Dialog Box

This dialog box enables you to view the progress of result collation after a scenario run.

<b>To access</b>	<ul style="list-style-type: none"> <li>• <b>Results &gt; Collate Results &gt; Collate Results</b></li> <li>• If <b>Auto Collate Results</b> is activated, this dialog box opens automatically when LoadRunner starts collating the run results after a scenario run.</li> </ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"> <li>• "<a href="#">How to Collate Scenario Run Results</a>" on page 1222</li> <li>• "<a href="#">How to Prepare a Scenario to Run</a>" on page 1185</li> </ul>

User interface elements are described below:

UI Element	Description
 Stop	Stops collating the results.
<b>Close automatically</b>	Select to automatically close the Collate Results dialog box after collation is completed.

<b>General Status</b>	The collation status and file size of the Event, Diagnostics, and Log files.  File size shown is before compression.
<b>Progress Details</b>	The status (succeeded, failed) of result, diagnostics, and log file collation from each load generator or mediator. This information is stored in the <b>collateLog.txt</b> file.

## Using QuickTest or Unified Functional Testing Tests in LoadRunner

### ***Using QuickTest or Unified Functional Testing Tests in LoadRunner - Overview***

HP Functional Testing software (QuickTest or Unified Functional Testing) enables you to create complex tests that examine the full spectrum of your application's functionality.

LoadRunner can integrate QuickTest or Unified Functional Testing tests into a load testing scenario in the form of GUI Vuser scripts. These tests, that have already been designed and debugged in QuickTest or Unified Functional Testing can be used as the basis of your load test.

The main uses of running QuickTest or Unified Functional Testing tests in LoadRunner are:

- To check how your application's functionality is affected by heavy load
- To measure the response time that a typical user experiences on the client side while your application is under load (end-to-end response time)

For example, you can add QuickTest or Unified Functional Testing tests to specific points in a LoadRunner scenario to confirm that the application's functionality is not affected by the extra load at those sensitive points.

Another advantage of using a GUI Vuser script as part of your LoadRunner scenario is that the GUI Vuser script runs on your screen during the scenario, enabling you to watch the actual steps executed by the Vuser in real time.

### ***About GUI Vuser Scripts***

GUI Vusers enable you to measure and monitor end-to-end user response times while your client/server system is under load. A GUI Vuser emulates the complete environment of a human user.

For example, a human user sits at a machine, operates applications using the keyboard and the mouse, and reads information on the machine's monitor. Similarly, a GUI Vuser runs on its own machine and operates applications. A GUI Vuser can be programmed to read and act on information that appears on its machine's display.

Suppose that you have a bank server that services many automatic teller machines (ATMs). You could create a GUI Vuser script that:

- Opens the ATM application
- Enters an account number
- Enters the amount of cash to be withdrawn
- Withdraws cash from the account
- Checks the balance of the account
- Closes the ATM application
- Repeats the process


The actions of each GUI Vuser are described in a GUI Vuser script. You use QuickTest or Unified Functional Testing to create GUI Vuser scripts.

You monitor and manage GUI Vusers using the LoadRunner Controller. For instance, you can use the Controller to run, pause, or view Vusers, and to monitor scenario status.

**Note:** You cannot use VuGen to run a GUI Vuser script. You use the Controller to run a GUI Vuser script as part of a scenario; you use QuickTest or Unified Functional Testing to run a GUI Vuser script in standalone mode.

## ***Understanding GUI Vuser Technology***

GUI Vusers measure real end-to-end response times. End-to-end response times represent the total time that a user waits for a response after submitting a request. End-to-end response times include GUI response times as well as network and server response times.



## ***Guidelines for Using QuickTest or Unified Functional Testing Tests in LoadRunner***

When creating test scripts in QuickTest or Unified Functional Testing that are going to be used as GUI Vuser scripts in a LoadRunner testing scenario, you need to follow certain guidelines to ensure smooth integration of the script. For detailed explanations about creating tests in QuickTest or Unified Functional Testing, see the QuickTest or Unified Functional Testing documentation.

### **Limitations**

QuickTest or Unified Functional Testing offers several features that are designed specifically for integration with LoadRunner. Some QuickTest or Unified Functional Testing features, however, may not be available when they are integrated with LoadRunner. For more information about specific limitations, see the QuickTest or Unified Functional Testing readme.

### **Including Transactions**

To measure the performance of the server, you define **transactions**. A transaction represents an action or a set of actions that you are interested in measuring. You define transactions within your Vuser script by enclosing the appropriate sections of the script with **start** and **end** transaction

statements.

For example, you can define a transaction that measures the time it takes for the server to process a request to view the balance of an account and for the information to be displayed at the ATM.

**Note:** LoadRunner only provides performance information for data that is included within a transaction. Therefore, your QuickTest or Unified Functional Testing test must include transactions to be used by LoadRunner.

For more information about using transactions in QuickTest or Unified Functional Testing, see the QuickTest or Unified Functional Testing documentation.

## Adding Statements

You can use the **Services** object and its associated methods to insert statements that are specifically relevant to performance testing. These include **Abort**, **GetEnvironmentAttribute**, **LogMessage**, **SetTransactionStatus**, **ThinkTime**, **UserDataTable**, **StartTransaction** and **EndTransaction**. For more information on these methods, see the QuickTest or Unified Functional Testing documentation.

## Designing Tests for LoadRunner

Consider the following design guidelines when designing tests for use with LoadRunner:

- The QuickTest or Unified Functional Testing tests you use with LoadRunner should be simple tests, designed to pinpoint specific operations.
- LoadRunner cannot run nested action iterations.
- Do not include references to external actions or other external resources, such as an external Data Table file, environment variable file, shared object repositories, and so forth.
- Include transactions in your QuickTest or Unified Functional Testing test since LoadRunner only provides performance information for data that is included within a transaction.

## **How to Add a QuickTest or Unified Functional Testing Test to a Load Test Scenario**

This task describes how to integrate a QuickTest or Unified Functional Testing test into LoadRunner.

1. Navigate to the folder containing the test.
  - For a new scenario, click **Browse** in the New Scenario dialog box.
  - When adding the test to an existing scenario, click **Browse** in the Add Group/Add Script dialog box. The Open Test dialog box opens.
2. In the **Files of Type** box select **QuickTest Tests** or **Unified Functional Testing Tests**.

3. Navigate to the appropriate test and add it to your scenario.

## Managing Scenarios Using Application Lifecycle Management

### ***Managing Scenarios Using Application Lifecycle Management - Overview***

The Controller works together with HP Application Lifecycle Management (ALM), HP's Web-based test management tool. HP ALM provides an efficient method for storing and retrieving Vuser scripts, scenarios, and results. You can store scenarios in an ALM project and organize them into unique groups.

In order for the Controller to access an ALM project, you must connect it to the Web server on which HP Application Lifecycle Management is installed. You can connect to either a local or remote Web server.

For more information on working with Application Lifecycle Management, see the *Application Lifecycle Management User's Guide*.

### ***How to Work with Scenarios in ALM Projects***

The following steps describe the workflow of how to work with scenarios saved in an Application Lifecycle Management project.

#### **1. Connect to ALM**

Open a connection to the ALM server and project that contains the scenario. For task details, see "[Connect to ALM](#)" below.

#### **2. Open the scenario**

Select **File > Open**. The Open Scenario from HP ALM Project dialog box opens. Select the name and location of the scenario to open.

#### **3. Save the scenario**

Select **File > Save as**. If the scenario is in a project that uses version control and is not checked out, the scenario is only saved as a temporary file on your local machine.

## **Connect to ALM**

To store and retrieve scenarios from ALM, you need to connect to an ALM project. You can connect or disconnect from an ALM project at any time during the testing process.

You can connect to one version of HP ALM from Controller and a different version from your browser. For more information, see the **Important Information** section in "[HP ALM Connection Dialog Box \[Controller\]](#)" on page 1231.

## Connect to Application Lifecycle Management

1. Select **Tools > HP ALM Connection**. The HP ALM Connection dialog box opens.
2. Enter the required information in the HP ALM Connection dialog box, as described in "[HP ALM Connection Dialog Box \[Controller\]](#)" on the next page.
3. To disconnect from ALM, click **Disconnect**.

## How to Save Scenarios to ALM Projects

The following steps describe how to save a scenario to an ALM project.

### 1. Open/create the scenario

Create or open the desired scenario.

### 2. Connect to HP Application Lifecycle Management

Open a connection to the ALM server and project in which you want to store the scenario. For task details, see "[Connect to ALM](#)" on the previous page.

### 3. Define a test set

Define an Application Lifecycle Management test set where to save results as follows:

- a. Select **Results > Results Settings**. The Set Results Directory dialog box opens.
  - b. Click **HP ALM**.
  - c. Enter the required information in the Set Results Directory dialog box. For user interface details, see "[Set Results Directory Dialog Box](#)" on page 1188.
  - d. Click **OK**.
- ### 4. Save the scenario to ALM
- Select **File > Save as** and specify the location.

## How to Add Vuser Scripts from an Application Lifecycle Management Project

The following steps describe how to add Vuser scripts from an Application Lifecycle Management project to the Controller's script list. You can add the script to either a manual or a goal-oriented scenario.

### 1. Add a Vuser script to a manual scenario

- a. Open a connection to the ALM server and project where the scripts are located. For task details, see "[Connect to ALM](#)" on the previous page.

- b. In the Scenario Groups pane, click the **Add Group** button .
- c. In the Add Group dialog box, click **Browse**. The Open Test from HP ALM Project dialog box opens.
- d. Select the script and click **OK**. The Script Path field displays [TD], the full subject path, and the script name.

For example:

[TD]\Subject\System\test\_alm

- e. Click **OK**. The script is displayed in the Scenario Groups pane.

## 2. Add a Vuser script to a goal-oriented scenario

- a. Open a connection to the ALM server and project where the scripts are located. For task details, see "[Connect to ALM](#)" on page 1229.
- b. On the Scenario Scripts pane toolbar, click the **Add Script**  button. The Add Script dialog box opens.
- c. Click **Browse**. The Open Test from HP ALM Project dialog box opens and displays the test plan tree.
- d. Select the script and click **OK**. The Script Path field displays [TD], the full subject path, and the script name.

For example:

[TD]\Subject\System\test\_alm

- e. Click **OK** to close the Add Script dialog box. The script appears in the Script Path column in the Scenario Scripts pane.

## **HP ALM Connection Dialog Box [Controller]**

This dialog box enables you to connect to an ALM project from within the Controller.

To access	Tools > HP ALM Connection
<b>Important information</b>	<p>You can connect to one version of HP ALM from Controller and a different version of HP ALM from your browser.</p> <p>You can only connect to different versions of HP ALM if one of the versions is HP ALM 11.00 or higher.</p> <p><b>Note:</b> Before you connect to results stored on ALM through this dialog box, it is recommended that you first connect to the HP ALM server through your browser. This automatically downloads the ALM client files to your computer.</p>

User interface elements are described below:

UI Element	Description
<b>Step 1: Connect to Server</b>	<ul style="list-style-type: none"> <li><b>Server URL.</b> The URL of the server on which ALM is installed.</li> <li><b>Reconnect to server on startup.</b> Automatically reconnect to the server every time you start the Controller.</li> <li> <b>Connect</b> /  <b>Disconnect</b>. Connects to the server specified in the <b>Server URL</b> box. Only one button is visible at a time, depending on your connection status.</li> </ul>
<b>Step 2: Authenticate User Information</b>	<p><b>Note:</b> Step 2 is only visible after you successfully connect to a server.</p> <ul style="list-style-type: none"> <li><b>User Name.</b> Your ALM user name.</li> <li><b>Password.</b> Your ALM password.</li> <li><b>Authenticate on startup.</b> Authenticates your user information automatically, the next time you open the application. This option is available only if you selected <b>Reconnect to server on startup</b> above.</li> <li> <b>Authenticate</b>. Authenticates your user information against the ALM server.</li> </ul> <p>After your user information has been authenticated, the fields in the Authenticate user information area are displayed in read-only format. The <b>Authenticate</b> button changes to  <b>Change User</b>. You can log in to the same ALM server using a different user name by clicking <b>Change User</b>, entering a new user name and password, and then clicking <b>Authenticate</b> again.</p>
<b>Step 3: Login to Project</b>	<ul style="list-style-type: none"> <li><b>Domain.</b> The domain that contains the ALM project. Only those domains containing projects to which you have permission to connect to are displayed.</li> <li><b>Project.</b> Enter the ALM project name or select a project from the list. Only those projects that you have permission to connect to are displayed.</li> <li><b>Login to project on startup.</b> This option is enabled only when the <b>Authenticate on startup</b> check box is selected.</li> <li> <b>Login</b> /  <b>Logout</b>. Logs into and out of the ALM project.</li> </ul>

## Working with Firewalls in LoadRunner

## Monitors Over a Firewall

To monitor servers over a firewall, you need to configure the Monitor Over Firewall machine. On the Monitor Over Firewall machine, you use the Server Monitor configuration tool to select which servers to monitor and to define specific measurements that LoadRunner collects for each monitored server.

To enable monitoring of your servers over a firewall, you install the Monitor Over Firewall component on a dedicated machine.

**Caution:** Before you configure your system to monitor your servers over a firewall, ensure that you have completed the configuration steps described in "[How to Configure the Over-Firewall System](#)" on the next page.

After you have set up your LoadRunner system to work with firewalls, you need to configure the monitor settings on the Monitor Over Firewall machine.

You use the Server Monitor configuration tool to select which servers to monitor and to define specific measurements that LoadRunner collects for each monitored server. For more information, see "[How to Configure Monitors Over a Firewall](#)" on page 1240.

**Tip:** The LoadRunner standalone Load Generator (LG SA) and standalone Monitor over Firewall (MOFW SA) cannot be installed on the same machine. However, LG SA can be used for monitoring purposes, the same way as the MOFW SA. Note that a single machine cannot be used simultaneously for both running Vusers and monitoring.

## How to Set Up Your System to Use Firewalls

Setting up your system to use firewalls involves the following stages of configuration:

### 1. Install Components and Perform Initial Configuration

Perform the following steps:

#### a. Install the over-firewall components.

To enable over firewall communication, ensure that you have installed the following LoadRunner components:

- **MI Listener.** Serves as a router between the Controller and the LoadRunner agent. You install the MI Listener component on a dedicated machine. For installation instructions, refer to the *HP LoadRunner Installation Guide*.

For instructions on configuring the MI Listener machine, see "[How to Configure the Over-Firewall System](#)" on the next page.

**Note:** You can also use the Controller machine as the MI Listener without the need for a separate installation. When acting as the MI Listener, the Controller machine cannot have Vusers running on it. In this case, the Controller must be a pure Controller and not a Controller + Load Generator.

- **Monitor Over Firewall component.** Used to monitor the servers that are located over a firewall. You install the Monitors over Firewall component on a dedicated machine. For installation instructions, refer to the *HP LoadRunner Installation Guide*.

For information about configuring the Monitor Over Firewall machine, see "[How to Configure Monitors Over a Firewall](#)" on page 1240.

b. **Perform the initial configuration of the over-firewall system.**

See "[How to Configure the Over-Firewall System](#)" below.

**2. Set Up Your System to Run Vusers Over the Firewall**

**Note:** Before configuring your system to run Vusers over a firewall, make sure that you have completed the steps described in "[How to Configure the Over-Firewall System](#)" below.

To set up your system to run Vusers over a firewall, you configure the LoadRunner agent to communicate with the MI Listener on each load generator machine that will be running over the firewall. For more information, see "[How to Configure the System to Monitor Servers Over a Firewall](#)" on page 1237.

You then configure the Controller to recognize the load generator and MI Listener machines. For more information, see "[How to Configure the System to Monitor Servers Over a Firewall](#)" on page 1237.

**3. Configure Your System to Monitoring Servers Over a Firewall**

See "[How to Configure the System to Monitor Servers Over a Firewall](#)" on page 1237.

**4. Check Connectivity**

After installing and configuring all the necessary components, check that you are able to establish a connection between the LoadRunner agent, MI Listener, and the Controller machine. For more information, see "[Troubleshooting and Limitations - Firewalls](#)" on page 1250.

## How to Configure the Over-Firewall System

This task describes how to configure the Over-Firewall System.

## 1. Prerequisites


Before configuring the over-firewall system, make sure you have installed the necessary components as described in ["How to Set Up Your System to Use Firewalls" on page 1233](#).

## 2. Set Up Your Deployment (TCP or HTTPS)

To run Vusers or monitor servers over the firewall, configure your system according to one of the following configurations. Note that these configurations contain a firewall on each LAN. There may also be configurations where there is a firewall for the Over-Firewall LAN only.


### ▪ TCP Configuration

The TCP configuration requires every LoadRunner agent machine behind the customer's firewall to be allowed to open a port in the firewall for outgoing communication.



### ▪ HTTPS Configuration

In the HTTPS configuration, only one machine (the proxy server) is allowed to open a port in the firewall. Therefore, it is necessary to tunnel all outgoing communications through the proxy server.



### 3. Configure the Firewall to Allow Agent Access

Modify your firewall settings to enable communication between the machines inside the firewall and machines outside the firewall.

a. **If your system has a TCP configuration:**

The LoadRunner agent attempts to establish a connection with the MI Listener using port 443, at intervals specified in the Connection Timeout field in the Agent Configuration dialog box. To enable this connection, allow an outgoing connection for HTTPS service on the firewall for port 443. The agent can then connect to the MI Listener, and the MI Listener can connect back to the agent. From this point on, the agent listens to commands from the MI Listener.

b. **If your system has an HTTPS configuration:**

The LoadRunner agent attempts to establish a connection with the MI Listener, using the proxy port specified in the Proxy Port field, and at intervals specified in the Connection Timeout field in the Agent Configuration dialog box. When the connection is established, the proxy server connects to the MI Listener. To enable this connection, allow an outgoing connection for HTTPS service on the firewall for port 443. The proxy server can then connect to the MI Listener, and the MI Listener can connect back to the agent through the proxy server. From this point on, the agent listens to commands from the MI Listener.

c. **If you intend to start the LR Agent service from the Local System account, you need to grant it permissions:**

If you do not provide permissions, the monitor graph will not display any data. Add a local user on the AUT machine with the same name and password as the local user on Agent machine. Add the AUT local user to the **Performance Monitor Users** group and restart the Agent process.

#### 4. Configure the MI Listener

To enable running Vusers or monitoring over a firewall, you need to install the MI Listener on one or more machines in the same LAN as the Controller outside the firewall. For installation instructions, see "[Additional Components](#)" on page 1741.

**Note:**

- The Controller installation automatically includes the MI Listener, so you can designate the Controller as the MI Listener machine.
- The MI Listener can only be installed on Windows machines.

For information on how to configure the MI Listener, see "[MI Listener Configuration Dialog Box](#)" on page 1247.

## How to Configure the System to Monitor Servers Over a Firewall

This task describes how to set up your system to monitor the servers over a firewall.

### 1. Prerequisites

Before configuring the system to monitor servers over a firewall, make sure that you have completed the task "[How to Configure the Over-Firewall System](#)" on page 1234.

To add Windows Resource counters from a remote machine, you need to log in with administrator permissions and start the Remote Registry service on the remote machine.

### 2. Configure the LoadRunner Agent on Each Monitor Over Firewall Machine

See "[How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine](#)" on the next page.

### 3. Configure the Controller for Running Over a Firewall

To run or monitor Vusers over a firewall, you need to create a unique connection between the Controller and the agent machines. Agent machines include load generator machines that will be running over a firewall and all Monitor Over Firewall machines.

This connection is made through the MI Listener, which serves as a router between the Controller and the LoadRunner agent. To establish this connection, you configure the Controller machine to define the agent machine as a load generator.

To configure the Controller for running Vusers or monitoring over the firewall, define the load generator settings as described in ["Load Generators Dialog Box" on page 1101](#). For the server name, be sure to use the same Local Machine Key setting as in the Agent Configuration.

Then, define the settings in the ["MI Listener Configuration Dialog Box" on page 1247](#), using the same MI Listener name as in the Agent Configuration.

**Note:** You cannot change the temporary folder on the host running or monitoring Vusers over the firewall.

#### 4. Enable and Confirm your Connection

After you have configured the LoadRunner Agent, the MI Listener and the Controller, select the load generator in the Load Generators window and click **Connect**.

A green or red light next to the LoadRunner agent in the system tray indicates a successful or unsuccessful connection respectively.

#### 5. Configure the Servers to Monitor and Define Measurements for Collection

You configure the monitor settings from the Monitor Over Firewall machine, using the Monitor Configuration tool (**Start > All Programs > HP Software > HP LoadRunner > Advanced Settings > Monitor Configuration**).

You select the type of monitors to run and the server whose resources you want to monitor, add the measurements to monitor for each server, and specify the frequency with which you want the monitored measurements to be reported.

For detailed information about how to use the Monitor Configuration tool, see ["How to Configure Monitors Over a Firewall" on page 1240](#).

## How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine

On each load generator machine that will be running over a firewall and on each Monitor Over Firewall machine, you configure the LoadRunner agent to communicate with the MI Listener. The MI Listener serves as a router between the LoadRunner agent and the Controller.

#### 1. Configure the Windows LoadRunner Agent

- a. Stop the LoadRunner agent by right-clicking its icon in the system tray and selecting **Close**, and then setting the options in the Agent Configuration dialog box as described in

"[Agent Configuration Dialog Box](#)" on page 1241.

- b. Restart the LoadRunner agent by double-clicking the shortcut on the desktop.

## 2. Configure and Run the Linux LoadRunner Agent

- a. Open <LoadRunner root folder>/dat/br\_Inch\_server.cfg in a text editor.
- b. In the Firewall section, set FireWallServiceActive to 1 and save your changes.
- c. Run **agent\_config** from the <LoadRunner root folder>/bin folder to display the following menu:

```
Menu:  
1. Show current settings.  
2. Change a setting.  
3. Save changes and exit.  
4. Exit without saving.  
5. Use default values.
```

**Note:** If **agent\_config** does not display the menu shown above, see "[Troubleshooting and Limitations - Firewalls](#)" on page 1250 for a possible solution.

- d. Enter 1 to display the current settings:

```
Settings:  
-----  
1. MI Listener Name =  
2. Local Machine Key =  
3. Connection Timeout (seconds) = 20  
4. Connection Type = TCP  
5. Use Secure Connection (SSL) = False  
6. Check Server Certificates = False  
7. Client Certificate Owner = False  
8. Private Key User Name =  
9. Private Key Password =  
10. Proxy Name =  
11. Proxy Port =  
12. Proxy User Name =  
13. Proxy Password =  
14. Proxy Domain =
```

```
Menu:  
1. Show current settings.  
2. Change a setting.  
3. Save changes and exit.  
4. Exit without saving.  
5. Use default values.
```

- e. To change a setting, enter 2 to display the settings menu:

```
Settings:  
-----  
1. MI Listener Name =  
2. Local Machine Key =  
3. Connection Timeout (seconds) = 20  
4. Connection Type = TCP  
5. Use Secure Connection (SSL) = False  
6. Check Server Certificates = False  
7. Client Certificate Owner = False  
8. Private Key User Name =  
9. Private Key Password =  
10. Proxy Name =  
11. Proxy Port =  
12. Proxy User Name =  
13. Proxy Password =  
14. Proxy Domain =  
  
Enter number of setting to change or 0 to go back to menu.
```

Enter the setting and continue according to the menu instructions. Set each option according to the ["Agent Configuration Settings Dialog Box" on page 1243](#).

- f. Restart the agent for the configuration changes to take effect.

### 3. Restart the LoadRunner Agent

- a. To remove the LoadRunner agent, run the command `m_daemon_setup -remove` from the `<LoadRunner root folder>/bin` folder.

**Note:** When the LoadRunner agent is configured to run over a firewall, and the agent is connected to the MI Listener, a file called `<local_machine_key>_connected_to_MI_Listener` is created in the temporary folder of the LoadRunner agent machine. The file is removed when the LoadRunner agent disconnects from the MI Listener.

- b. To start the LoadRunner agent, run the command `m_daemon_setup -install` from the `<LoadRunner root folder>/bin` folder.

## How to Configure Monitors Over a Firewall

After you have installed and configured the LoadRunner agent, the Monitors over Firewall component, the MI Listener, and the Controller machine, you need to choose the server measurements that you want the Monitor Over Firewall machine to monitor.

You configure the server monitor properties from the Monitor Over Firewall machine, using the ["Monitor Configuration Dialog Box" on page 1248](#). You can select the type of monitors to run and the server whose resources you want to monitor, add the measurements to monitor for each server, and specify the frequency with which you want the monitored measurements to be reported.

The following steps describe how to configure monitors over a firewall:

## 1. Open the Monitor Configuration Dialog Box

Select **Start > All Programs > HP Software > HP LoadRunner > Advanced Settings > Monitor Configuration**. For machines without the complete LoadRunner installation, select **Start > Programs > Server Monitor > Monitor Configuration**.

## 2. Add Monitored Servers

- To add servers, click the **Add Server** button . Type the name or IP address of the server whose resources you want to monitor in the **Monitored Server** field.

**Note:** To add several servers simultaneously, separate the server names or IP ranges with commas. For example: 255.255.255.0-255.255.255.5, server1, server2.

- From the Available Monitors list, select the monitors appropriate for the server being monitored.

**Note:** Data can only be viewed for the monitors that are enabled with your LoadRunner license key. To preview your license key information, select **Start > Programs > HP Software > HP LoadRunner > License > LoadRunner License Utility**.

For certain monitors, LoadRunner displays default measurements in the Measurements to be Monitored section. You can specify the frequency at which LoadRunner reports the measurement in the Measurement Properties section. For details on selecting measurements, see "[How to Set Up a Monitoring Environment](#)" on page 1259.

## 3. (Optional) Clone a Monitored Server's Properties

If you want to monitor the same properties on different server machines, you can clone a selected server's properties using the Clone Monitored Server Properties dialog box.

To clone a monitored server's properties, right-click the server you want to clone, and select **Clone**. In the Monitored Server box, type the name or IP address of the clone server you want to create.

# Agent Configuration Dialog Box

This dialog box enables you to open the Agent Configuration Settings dialog box in order to configure the LoadRunner agent on Windows machines.

<b>To access</b>	<ul style="list-style-type: none"><li>• <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Advanced Settings &gt; Agent Configuration</b></li><li>• Run &lt;LoadRunner root&gt;\launch-service\bin\AgentConfig.exe</li></ul>
------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	<ul style="list-style-type: none"> <li>The Agent icon does not appear in Windows 2008 when the LoadRunner Agent service is launched.</li> <li>When LoadRunner Agent runs as service (magentservice.exe), files that are stored on remote network drives or referred to by UNC path cannot be accessed (script, parameter file, etc.). If you want to access files this way, run the LoadRunner Agent as process (magentproc.exe).</li> </ul> <p><b>Workaround:</b> To access network share, configure the LoadRunner Agent service to run with an account that has network access permissions.</p> <ul style="list-style-type: none"> <li>When running the LoadRunner Agent as a service (magentservice.exe), and the Agent Configuration as administrator under UAC or a standard user: If you click the <b>OK</b> button and attempt to restart the LoadRunner Agent service, it issues the warning "Access is denied".</li> </ul> <p><b>Workaround:</b></p> <ol style="list-style-type: none"> <li>Run the Agent Configuration as administrator when UAC is on.</li> <li>If the current user is administrator, or a user having the appropriate permission to work with LoadRunner Agent services, go to Service Manager (services.msc), and manually start the LoadRunnerAgent service (and for Performance Center, the RemoteManagementAgent service).</li> <li>You can also run &lt;LR&gt;\bin\subinacl.exe as administrator to grant a user (user1 in examples below) full access permission of the target service. For example,</li> </ol> <p><b>For LoadRunner:</b> subinacl.exe /service LoadRunnerAgent /grant=user1</p> <p><b>For Performance Center:</b> subinacl.exe /service RemoteManagementAgent /grant=user1</p>
<b>Relevant tasks</b>	<a href="#">"How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine" on page 1238</a>
<b>See also</b>	<a href="#">"Agent Configuration Settings Dialog Box" on the next page.</a>

User interface elements are described below:

UI Element	Description
<b>Enable Firewall Agent</b>	Select if you are enabling or running Vusers over a firewall.
	Enabled only when the Enable Firewall Agent check box is selected. Click to open the Agent Configuration Settings dialog box.
<b>Enable Terminal Services</b>	Select to enable distributing Vusers on a terminal server.

## Agent Configuration Settings Dialog Box

This dialog box enables you to define the relevant settings in order to enable the LoadRunner agent on Windows machines.

<b>To access</b>	<b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Advanced Settings &gt; Agent Configuration &gt; Settings</b>
<b>Relevant tasks</b>	"How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine" on page 1238
<b>See also</b>	"Agent Configuration Dialog Box" on page 1241
<b>Important information</b>	The new Agent configuration tool provides greater flexibility for defining the agent settings through the command line. For details, see "Network and Security Manager - Command Line Tool" on page 1108.

User interface elements are described below:

UI Element	Description
<b>MI Listener Name</b>	The name, full name, or IP address of the MI Listener.
<b>Local Machine Key</b>	A symbolic string identifier used to establish a unique connection between the Controller host and the agent machine, via the MI Listener machine.
<b>Connection Timeout (seconds)</b>	The length of time you want the agent to wait before retrying to connect to the MI Listener machine. If zero, the connection is kept open from the time the agent is run. <b>Default value:</b> 20 seconds
<b>MI Listener User Name</b>	The user name needed to connect to the MI Listener machine.
<b>MI Listener Password</b>	The password needed to connect to the MI Listener machine.
<b>Server Domain</b>	The domain name needed to connect to the MI Listener machine. This field is required only if NTLM is used.
<b>Connection Type - TCP/HTTP</b>	Select either <b>TCP</b> or <b>HTTP</b> , depending on the configuration you are using. <b>Default:</b> TCP
<b>Connection Type - HTTP Proxy Name</b>	The name of the proxy server. This field is mandatory if the <b>Connection Type</b> setting is <b>HTTP</b> .

UI Element	Description
<b>Connection Type - HTTP Proxy Port</b>	The proxy server connection port. This field is mandatory if the <b>Connection Type</b> setting is <b>HTTP</b>
<b>Connection Type - HTTP Proxy User Name</b>	The user name of a user with connection rights to the proxy server.
<b>Connection Type - HTTP Proxy Password</b>	The password of the user with connection rights to the proxy server.
<b>Connection Type - HTTP Proxy Domain</b>	The user's domain if defined in the proxy server configuration. This option is required only if NTLM is used.
<b>Use Secure Connection (SSL)</b>	Enable to connect using the Secure Sockets Layer protocol. <b>Default:</b> disabled
<b>Use Secure Connection (SSL) - Check Server Certificates</b>	Authenticates the SSL certificates that are sent by the server. Select <b>Medium</b> to verify that the server certificate is signed by a trusted Certification Authority. Select <b>High</b> to verify that the sender IP matches the certificate information. This setting is available only if <b>Use Secure Connection</b> is enabled.
<b>Use Secure Connection (SSL) - Private Key Password</b>	The password that might be required during the SSL certificate authentication process. This option is relevant only if the <b>Client Certificate Owner</b> option is enabled.
<b>Use Secure Connection (SSL) - Use Client Certificate</b>	Enable to load the SSL certificate (if required by the server to allow the connection to be made). This setting is available only if <b>Use Secure Connection</b> is enabled. <b>Default:</b> disabled

## Authentication Settings Dialog Box

This dialog box enables you to select a certificate for your scenario run, or create one automatically.

To access	Controller > Tools > Authentication Settings
-----------	----------------------------------------------

<b>Important information</b>	Once you create a CA certificate, you must use it for all of the LoadRunner components.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• <a href="#">"How to Change a Certificate" on page 1338</a></li><li>• <a href="#">"How to Create and Use Digital Certificates" on page 1346</a></li></ul>

User interface elements are described below:


UI Element	Description
<b>CA certificate file</b>	The CA certificate file (with a .cer extension).
<b>Generate a certificate automatically</b>	Generates an SSL certificate based on the common name and CA private key. For more options, click <b>Advanced settings</b> .
<b>Choose an existing certificate file</b>	The SSL certificate file (with a .cer extension). This certificate will be sent to a load generator or MI Listener with enforced SSL client authentication. Only a certificate issued on the other end by the same CA, will be trusted,

## MI Listener and Over Firewall Overview


In communication using client-server authentication, you must set the certification flag on the **server** machine using the ["Network and Security Manager - Command Line Tool" on page 1108](#). This forces the client machines to comply with the server certificates. For this reason, you need to determine which machine is the server.

The following images illustrate three possibilities:

- **Controller and Load Generator.** In this environment, the load generator machine is the server and the Controller is the client. You activate the authentication on the load generator, and this enforces the security between the machines.




- **Working with MI Listener and Controller.** In this environment, the MI Listener machine is the server and the Controller and load generators are the clients. You activate the authentication on the MI Listener machine and this enforces the security facing the Controller and load generators.



- **Working with Monitors over Firewall and MI Listener.** As in the previous environment, in this layout the MI Listener machine is the server. The Monitor over Firewall, Controller, and load generators machines are the clients. Once you activate authentication on the server—the MI Listener, it enforces the security on the other machines.

## Controller – MIL - LG & MOFW Communication



## MI Listener Configuration Dialog Box

This dialog box enables you to configure the MI Listener.

**To access**

- Select **Start > All Programs > HP Software > HP LoadRunner > Advanced Settings > MI Listener Configuration>**
- Run **<LoadRunner root folder>\launch\_service\bin\MILsnConfig.exe**


<b>Important information</b>	<ul style="list-style-type: none"><li>• Before configuring the MI Listener:<ul style="list-style-type: none"><li>▪ Open incoming HTTPS service for port 443. The port settings are set by your system administrator.</li><li>▪ Stop the LoadRunner agent on the MI Listener machine by right-clicking its icon in the system tray and selecting <b>Close</b> from the popup menu.</li></ul></li><li>• After configuring the MI Listener:<ul style="list-style-type: none"><li>▪ Restart the LoadRunner agent by double-clicking the shortcut on the desktop, or by selecting <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Advanced Settings &gt; Agent Service</b>.</li><li>• Make sure that no Web Servers are running on the MI Listener or Monitor over Firewall machine. These servers use port 443 and will not allow the access required by the listening and monitoring processes.</li></ul></li></ul>
<b>Relevant tasks</b>	<a href="#">"How to Configure the Over-Firewall System" on page 1234</a>

User interface elements are described below:

UI Element	Description
<b>Check Client Certificates</b>	Select <b>True</b> to request that the client send an SSL certificate when connecting, and to authenticate the certificate. Default value is <b>False</b> .
<b>Private Key Password</b>	The password that may be required during the SSL certificate authentication process. There is no default value.

## Monitor Configuration Dialog Box

This dialog box enables you to select the type of monitors to run and the server whose resources you want to monitor, add the measurements to monitor for each server, and specify the frequency with which you want the monitored measurements to be reported.



<b>To access</b>	<b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Advanced Settings &gt; Monitor Configuration.</b> For machines without the complete LoadRunner installation, select <b>Start &gt; All Programs &gt; Server Monitor &gt; Monitor Configuration.</b>
<b>Relevant tasks</b>	<a href="#">"How to Configure Monitors Over a Firewall" on page 1240</a>

User interface elements are described below:

UI Element	Description
------------	-------------

	Adds a server (left pane) or measurement (right pane) to the monitored server list. Type the name or IP address of the server whose resources you want to monitor in the <b>Monitored Server</b> field. <b>Note:</b> To add several servers simultaneously, separate the server names or IP ranges with commas. For example: 255.255.255.0-255.255.255.5, server1, server2. From the Available Monitors list, select the monitors appropriate for the server being monitored. <b>Note:</b> Data can only be viewed for the monitors that are enabled with your LoadRunner license key. To preview your license key information, select <b>Start &gt; Programs &gt; LoadRunner</b> . HP LoadRunner opens. Click the <b>License</b> button to display the LoadRunner license information.
	Removes a server or measurement.
	Opens the Monitored Server Properties dialog box, allowing you to modify the settings.
<b>Measurement Properties pane</b>	Allows you to set a measurement schedule for each measurement to be reported. Select the configured server measurement you want to schedule and specify the frequency at which you want LoadRunner to report the measurement. Click <b>Apply</b> to save your settings.
<b>Import / Export</b>	Imports or exports the monitor configuration details, including the server and their measurements, to/from an XML file.


## Troubleshooting and Limitations - Firewalls




This section describes troubleshooting for working with firewalls in LoadRunner.

### Checking Connectivity


To run Vusers or monitor servers over a firewall, you must be able to establish a connection between the LoadRunner agent, MI Listener, and the Controller machine.

If you encounter connectivity problems after installing and configuring all the necessary components, check the table below for troubleshooting tips.

Check	Solution
To check that the Firewall service was activated on the agent machine:  	There should be a traffic light on the right side of the LoadRunner Agent icon on the machine running/ monitoring Vusers over a firewall. If there is no traffic light, this indicates that the 'FirewallServiceActive=1' is not set in the [FireWall] section of the Agent Settings. See " <a href="#">Agent Configuration Settings Dialog Box</a> " on page 1243.

<p>To check that port 443 is open:</p>  <p>MI Listener Machine → Firewall (Port 443) ← Load Generator/Agent Machine</p>	<p>On the agent machine, open a Command Prompt window, and type the following: telnet &lt;MI_Listener_IP&gt;443. For example: telnet 111.111.111.1111 443. If port 443 is open, a new Telnet window will open. If port 443 is not open, contact your network administrator.</p>
<p>To check that port 443 is available:</p>  <p>Web server (X) → Firewall (Port 443) ← Load Generator/Agent Machine</p>	<p>If a Web server is running on the MI Listener or Monitor over Firewall machine, port 443 will not allow the access required by the listening and monitoring processes. Contact your network administrator to change the Web server port.</p>
<p>To check connectivity between the agent and the MI Listener, when running the LoadRunner agent as a service:</p>  <p>MI Listener Machine → Firewall (Port 443) ← Load Generator/Agent Machine</p>	<p>If there is a red light on the right side of the LoadRunner Agent icon  when running the LoadRunner agent as a service, do the following:</p> <ul style="list-style-type: none"> <li>Check that port 443 is open. See the troubleshooting tip "<a href="#">Troubleshooting and Limitations - Firewalls</a>" on the previous page.</li> <li>Check that the Agent Settings and Agent Configuration are correctly set. See "<a href="#">Agent Configuration Settings Dialog Box</a>" on page 1243.</li> <li>Run the agent as a Process. Launch <code>&lt;Installation&gt;\Launch_service\bin\magentproc.exe</code>. If this works, this indicates an authentication issue with the LoadRunner Agent Service. Browse to the <b>Service &gt; LoadRunner Agent Service</b>, and change the properties of this service to System User Account or provide the user name and password of someone who has administrative privileges on this machine.</li> </ul>

To check connectivity between the agent and the Controller, when monitoring over a firewall



- Check that you entered the servers that you want to monitor in the Monitor Configuration dialog box. (See "[Monitor Configuration Dialog Box](#)" on page 1248).
- Start the LoadRunner Agent Process on the Monitor Over Firewall machine. (See "[How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine](#)" on page 1238).
- On the Controller, enter the name of the Monitor Over Firewall machine in the Load Generators dialog box, and click **Connect**. After about a minute, data should start streaming in from the Monitor Over Firewall machine through the MI Listener to the Controller. (See "[How to Configure Monitors Over a Firewall](#)" on page 1240).
- If no data arrives at the Controller, try connecting the Controller to the MI Listener as if the Listener were used as a load generator. This will help identify the cause of the problem. Examine the log file on the Monitor Over Firewall machine by right-clicking the LoadRunner Agent icon. There should be no error messages.
- Start the MI Listener, and then manually start the LoadRunner Agent Process by running `<installation>\launch_service\bin\magnetproc.exe` on the Monitor Over Firewall machine. Allow the Monitor Over Firewall machine sufficient time to connect to the MI Listener, then connect the Controller to the Monitor Over Firewall machine. If the LoadRunner Agent Process crashes, either restart the agent or reboot the Monitor Over Firewall machine.

#### Windows Firewall Considerations

- In most Windows environments, Windows Firewall is turned on by default. The firewall does not

allow certain LoadRunner components to communicate with each other. The Windows firewall therefore needs to be turned off.

**Note:** Turning off Windows Firewall increases the risk to your computer's security.

- For each process that needs the firewall you can unblock the process by clicking the unblock button in the popup window that indicates that the program needs it, or by manually tuning the Windows firewall from the Exceptions tab.

### **agent\_config does not show the required menu**

When you configure the Linux LoadRunner Agent, you must run **agent\_config** to display the following menu:

```
Menu:  
1. Show current settings.  
2. Change a setting.  
3. Save changes and exit.  
4. Exit without saving.  
5. Use default values.
```

For details, see "[How to Configure the LoadRunner Agent on Each Monitor Over Firewall Machine](#)" on page 1238. If the menu does not display, type the following command to check if the M\_LROOT environment variable is set:

```
echo $M_LROOT
```

If M\_LROOT is not set, do either of the following:

1. Type sudo su - to inherit all environment variables of the current user.
2. Type source <LoadGenerator\_directory>/env.sh to set all the Load Generator related environment variables after switching to root (i.e. "sudo su").

**Note:** This limitation occurs on Amazon cloud Linux machines, usually when you log in to the system using the special user named "ec2-user".

## **Working with Diagnostics**

**Note:** The following protocols are supported by Diagnostics: Web (HTTP/HTML), Java Over HTTP, Oracle Web Applications 11i, SAP (Click & Script), SAP - Web, Siebel - Web, TruClient Firefox, AJAX (Click & Script), Web Services, and Flex.

### **Configuring J2EE/.NET Diagnostics**

## J2EE/.NET Diagnostics Overview

The HP Diagnostics integration with LoadRunner allows you to monitor and analyze the performance of Java 2 Enterprise Edition (J2EE), .NET-connected, SAP, Oracle, and other complex environments.

For more information about working with diagnostics for J2EE and .NET, see the *HP Diagnostics User Guide*.

## Monitoring Server Requests

When configuring a LoadRunner scenario to use J2EE/.NET Diagnostics, you can instruct LoadRunner to capture a percentage of server requests which occur outside the context of any Vuser transaction.

The benefit of enabling this functionality is that calls into a back-end VM can be captured even in the case where:

- The probe is not capturing RMI calls
- RMI calls cannot be captured (perhaps because an unsupported application container is being used)
- The application uses some other mechanism for communications between multiple VMs

## How to Specify J2EE/.NET Diagnostics Server Details

The first time you use LoadRunner to capture J2EE or .NET diagnostics data, you need to identify the machine on which the Diagnostics Server in Commander mode is running, and the port that it is using for communication with LoadRunner.

**Note:** You must update this information if you want to integrate with a different Diagnostics Server in Commander mode, or if you change the port it is using.

Update the LoadRunner configuration settings for HP Diagnostics

In the HP Diagnostics Commander, enter the details for the Diagnostics Server in Commander mode. For user interface details, see "[Diagnostics for J2EE/.NET Setup Dialog Box](#)" on page 1256.

## How to Configure a LoadRunner Scenario to use J2EE/.NET Diagnostics

This task describes how to capture J2EE/.NET diagnostics metrics in a LoadRunner scenario and how to select the probes that will be included in the scenario.

## 1. Prerequisite

- Start application server.

Make sure that the application server you are monitoring has already been started.

- Make sure that the load test scenario is not already running.

You must configure J2EE/.NET diagnostics before running the load test scenario.

## 2. Enable J2EE/.NET Diagnostics

Perform the following steps:

- In the Controller, select **Diagnostics > Configuration** to open the Diagnostics Distribution dialog box. Then select **Enable the following diagnostics** and specify the percentage of Vusers for which you want to collect J2EE/.NET Diagnostics data. For user interface details, see "[Diagnostics for J2EE/.NET Setup Dialog Box](#)" on the next page.
- In the Diagnostics Distribution dialog box, click **Configure** by J2EE/.NET Diagnostics to enable the module. For user interface details, see "[J2EE/.NET Configuration Dialog Box](#)" on page 1257.

## **How to View J2EE/.NET Diagnostics Data in LoadRunner During a Scenario Run**

This task describes how to view diagnostics data for J2EE/.NET Diagnostics in LoadRunner for the whole scenario or for a specific transaction during a scenario run.

### **View diagnostics data for the whole scenario**

In the Controller, select the **Diagnostics for J2EE/.NET** tab. HP Diagnostics opens, displaying the **Scenario Summary** dashboard view.

The **Scenario Summary** dashboard view displays monitoring versions of the transactions, server requests, load, and probe views for the current run.

**Note:** If you move to another tab during the scenario run and then return to the **Diagnostics for J2EE/.NET** tab, the last screen that you viewed will be displayed.

### **View Diagnostics Data for a Specific Transaction**

Perform the following steps:

1. Select one of the Transaction graphs (for example, **Transaction Response Time**), to open the graph.
2. Right-click the relevant transaction in the graph legend and select **Show J2EE/.NET server side**.

HP Diagnostics opens, displaying the Transactions view, which contains performance metrics and drill-down options for the selected transaction.

For more information about interpreting data in the Diagnostics Transactions view, see the *HP Diagnostics User Guide*.

## How to View Offline J2EE/.NET Diagnostics Results

### 1. Open Analysis

In the Run tab of the Controller, select **Results > Analyze Results**, or click the **Analyze Results** button .

### 2. View results in the Analysis diagnostics graphs

You can use the Analysis diagnostics graphs and reports to view the performance data and drill down to pinpoint problem areas in any layer of the application.

For specific information about J2EE/.NET diagnostics graphs, see "[J2EE & .NET Diagnostics Graphs Overview](#)" on page 1708.

## Diagnostics for J2EE/.NET Setup Dialog Box

This dialog box enables you to update the LoadRunner configuration settings for HP Diagnostics.

To access	<b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Tools &gt; Diagnostics for J2EE/.NET Setup</b>
Relevant tasks	<a href="#">"How to Specify J2EE/.NET Diagnostics Server Details" on page 1254</a>

User interface elements are described below:

UI Element	Description
<b>Test</b>	Click to verify that you entered the correct information for the Diagnostics Server in Commander mode and that there is connectivity between the server and LoadRunner.
<b>Login</b>	The user name with which you log in to Diagnostics. <b>Default:</b> admin <b>Note:</b> The user name that you specify should have <b>view</b> , <b>change</b> , and <b>execute</b> privileges. For more information about user privileges, see the <i>HP Diagnostics Server Installation and Administration Guide</i> .
<b>Password</b>	Enter the password with which you log in to Diagnostics. <b>Default:</b> admin

UI Element	Description
<b>Port</b>	Enter the port number used by the Diagnostic server in Commander mode. <b>Default:</b> 2006 <b>Note:</b> LoadRunner does not support communication with the Diagnostics Server in Commander mode using HTTPS.
<b>Server Name</b>	Enter the name of the machine that is to host the Diagnostics Server in Commander mode.

## J2EE/.NET Configuration Dialog Box

This dialog box enables you to set up the J2EE/.NET Diagnostics module.

<b>To access</b>	Select <b>Diagnostics &gt; Configuration</b> . Click <b>Configure by J2EE/.NET Diagnostics</b> .
<b>Important information</b>	The dialog box is read only while a scenario is running.
<b>Relevant tasks</b>	<a href="#">"How to Configure a LoadRunner Scenario to use J2EE/.NET Diagnostics" on page 1254</a>
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

User interface elements are described below:

UI Element	Description
<b>Enable J2EE/.NET Diagnostics</b>	Enables J2EE/.NET Diagnostics and allows you to configure the J2EE/.NET Diagnostics settings
<b>Select probes table</b>	<input type="checkbox"/> <b>Selects a probe for monitoring.</b> At least one probe must be selected. Clear the check box to disable a probe for the duration of the scenario. <b>Name.</b> The name of the probe. <b>Group.</b> The probe group. <b>Host Name.</b> The host the probe is running on (or the application server on which the probe is installed) is. <b>Note:</b> If you upgraded your Diagnostics installation, probes from existing scenarios may appear with a red status. Clear any probes that appear in red.
<b>There is a firewall between the Mediator and the Controller</b>	Select if the Diagnostics server (or a Diagnostics server in Mediator mode in a distributed environment) is located behind a firewall. <b>Note:</b> If there is a firewall between the LoadRunner Controller and the Diagnostics Server involved in a load test, you must configure the Controller and the Diagnostics Server to use the MI Listener to enable the transfer of the offline analysis file. For more information, refer to the <i>HP Diagnostics LoadRunner and Performance Center-Diagnostics Integration Guide</i> .

<b>MI Listener server</b>	Enter the name of the MI Listener server when the Diagnostics server (or a Diagnostics server in Mediator mode in a distributed environment) is located behind a firewall.
<b>Monitor server requests</b>	Select to capture a percentage of server requests which occur outside the context of any Vuser transaction. For more information, see " <a href="#">Monitoring Server Requests</a> " on page 1254. <b>Notes:</b> <ul style="list-style-type: none"><li>The server requests will be captured at the same percentage that was selected for the percentage of Vusers in the Diagnostics Distribution dialog box.</li><li>Enabling this option imposes an additional overhead on the probe.</li></ul>
<b>Troubleshoot Diagnostics for J2EE/.NET connectivity</b>	Click to open the HP Diagnostics System Health Monitor to enable you to investigate any connectivity issues between the Diagnostics components.

## Monitoring Load Test Scenarios

### HP Performance Monitoring Best Practices Guide


HP Performance Monitoring Best Practices Guide provides best practices for implementing performance monitoring using HP LoadRunner.

To view this guide in PDF format, go to **Start > All Programs > HP Software > HP LoadRunner > Documentation > Performance Monitoring Best Practices**.

## Working with LoadRunner Online Monitors

### ***Monitoring Process Overview***

Before monitoring a scenario, you need to set up and configure the LoadRunner monitoring components. Each monitor has different configuration requirements that are explained in the specific monitoring chapters. The following diagram illustrates the LoadRunner monitoring process.




Before monitoring a server, perform the following steps:

- Configure the monitoring environment on the server machine (if necessary).
- Configure the monitor on the Controller machine.

For details, see "[How to Set Up a Monitoring Environment](#)" below.

## **How to Set Up a Monitoring Environment**



This task describes how to set up the LoadRunner online monitoring environment. You specify the machines and measurements that the Controller will monitor during a scenario execution in the Controller's Run tab. During scenario execution, the collected measurement data appears in the online graphs.

### **Configure the monitoring environment on the server machine**

To use the following monitors, you must first install or configure monitoring components on the server machine. For details about configuring the monitoring components, see the specific monitoring sections.

- "[How to Set up the Citrix Monitoring Environment](#)" on page 1309
- "[How to Set Up the IBM WebSphere MQ Monitor](#)" on page 1316
- "[How to Configure a LoadRunner Scenario to use J2EE/.NET Diagnostics](#)" on page 1254
- "[How to Set Up the Network Monitoring Environment](#)" on page 1278

- "How to Set Up the Oracle Monitoring Environment" on page 1291
- "How to Set up the UNIX Monitoring Environment" on page 1274

**Note:** For information on how to set up the SiteScope monitoring environment, refer to the SiteScope documentation.

## Add the monitored server to the Controller

Select the server whose monitors you want to configure.

To monitor a server from the Controller, you need to add the machine and the measurements that you want to monitor.

1. Click the desired monitor graph in the graph tree, and drag it into the right pane of the Run tab.
  - Some monitors are native LoadRunner monitors (by default), but you can also monitor through the SiteScope monitor engine. To monitor through the SiteScope monitor, double-click it in the **Sitescope Graphs** node.
2. Right-click the graph and select **Add Measurements**, or click anywhere on the graph and select **Monitors > Add Measurements**. The <Monitor> dialog box opens.
3. In the **Monitored Server Machines** section of the <Monitor> dialog box, click **Add**. The Add Machine dialog box opens.
  - Enter the server name or IP address of the machine you want to monitor. Select the platform on which the machine runs.
  - For SiteScope monitors, enter the name and port number of the SiteScope server, and specify whether you are using a Secure HTTP connection. You can also provide different user credentials. For details, see "[Add Machine Dialog Box](#)" on page 1263.

## Select the measurements that you want to monitor

1. Make sure that the monitor you are configuring is selected in the **Monitored Server Machines** area of the <Monitor> dialog box.
2. In the **Resource Measurements** section of the <Monitor> dialog box, click **Add**. The <monitor> Configuration dialog box opens. Choose the measurements for the specific server.

**Note:** For the Citrix monitor, if the dialog box freezes after clicking **Add**, you may need to rebuild the localhost cache on the Citrix server machine.

For user interface details, see "[<Monitor Type> Monitor Configuration Dialog Box](#)" on page 1264.

For details about each monitor's default measurements, refer to the relevant reference section for the monitor.

## Change the monitor's default counters - Optional


When you configure the System Resource, Microsoft IIS, Microsoft ASP, and SQL Server monitors, you are presented with a list of default counters that you can measure on the server you are monitoring. You can change the default counters for these monitors by editing the **res\_mon.dft** file found in the **LoadRunner\dat** folder.

1. Open a new scenario and click the **Run** tab.
2. For each of the monitors, select the counters you want to measure.
3. Save the scenario and open the scenario **.lrs** file and **res\_mon.dft** file with an editor.
4. From the scenario **.lrs** file, copy the **MonItemPlus** section of the each counter you selected into the **res\_mon.dft** file.
5. Count the number of new counters in the **res\_mon.dft** file and update the **ListCount** parameter with this number.

## Improve the level of measurement information - Optional

You can improve the level of measurement information for the SNMP, iPlanet (SNMP), or Check Point FireWall-1 monitor by enabling measurements with string values to be listed (in addition to measurements with numeric values), and by enabling the name modifier (which displays the string value as an identifying part of the measurement name).

In the following example of a measurement using the name modifier, the string value of ProcessName (sched) is displayed in addition to its instance ID (0):



To enable this feature, add the following line to the **snmp.cfg** file in the **LoadRunner\dat\monitors** folder:

```
SNMP_show_string_nodes=1
```

**Note:** You can select more than one name modifier, but the first in the hierarchy will be used. Each time the SNMP Add Measurements dialog box opens, the information is reread from the **snmp.cfg** file. You cannot add the same measurement twice (once with a name modifier and once without it). If you do so, an error message is issued.

You can modify the list of resources that you want to monitor at any point during the scenario run. A scenario does not have to be active in order for you to monitor the resources on a remote machine.

## Monitor Types

All of the monitors allow you to view a summary of the collected data at the conclusion of the scenario. Using LoadRunner Analysis, you can generate a graph for any of the monitors. For more information, see ["Analysis Graphs" on page 1459](#).

The online monitors are divided into the following categories:

<b>Runtime Monitors</b>	Display the number and status of Vusers participating in the scenario, as well as the number and types of errors that the Vusers generate. For more information, see <a href="#">"Runtime and Transaction Monitoring" on page 1266</a> .
<b>Transaction Monitors</b>	Display the transaction rate and response times. For more information, see <a href="#">"Runtime and Transaction Monitoring" on page 1266</a> .
<b>Web Resource Monitors</b>	Provide information about the number of Web connections, throughput volume, HTTP responses, server retries, and downloaded pages at the Web servers during the scenario run. For more information, see <a href="#">"Web Resource Monitors" on page 1268</a> .
<b>System Resource Monitors</b>	Measure the Windows, Linux, Server, and SNMP resources used during a scenario run. For more information, see <a href="#">"System Resource Monitoring" on page 1273</a> .
<b>Network Monitors</b>	Displays information about the network delays on your system. For more information, see <a href="#">"Network Delay Monitoring" on page 1277</a> .
<b>Web Server Resource Monitors</b>	Measure statistics related to the Microsoft IIS and Apache Web servers during the scenario run. For more information, see <a href="#">"Web Server Resource Monitoring" on page 1286</a> .
<b>Web Application Server Resource Monitors</b>	Measure statistics related to the Microsoft ASP and WebLogic (SNMP) application servers during the scenario run. For more information, see <a href="#">"Web Application Server Monitoring" on page 1289</a> .
<b>Database Server Resource Monitors</b>	Measure statistics related to Oracle and SQL server databases during the scenario run. For more information, see <a href="#">"Database Server Resource Monitoring" on page 1290</a> .
<b>Shunra Network Virtualization Monitors</b>	Measure statistics related to Shunra network virtualization, such as Packet Loss and Latency. For information, see <a href="#">"Shunra Network Virtualization Monitoring" on page 1296</a> .
<b>Service Virtualization Monitors</b>	Measure statistics related to HP Service Virtualization, per operation and service. For information, see <a href="#">"Service Virtualization Monitoring Overview" on page 1325</a> .

<b>SiteScope Monitor</b>	Use the SiteScope monitor and its counters to measure resources. For information, see the documentation provided with SiteScope.
<b>Flex Monitors</b>	Measure statistics related to Flex RTMP connections and throughput, as well as buffering time. For details, see " <a href="#">Flex Monitoring</a> " on page 1304.
<b>Streaming Media Monitors</b>	Measure statistics related to the RealPlayer Client and Media Player Client servers during the scenario run. For more information, see " <a href="#">Streaming Media Monitoring</a> " on page 1304.
<b>ERP/CRM Server Resource Monitors</b>	Measure statistics related to the Siebel Server Manager Web server during the scenario run. For more information, see " <a href="#">ERP/CRM Server Resource Monitoring</a> " on page 1306.
<b>Application Deployment Solutions Monitors</b>	Measures statistics related to the Citrix server during a scenario run. For more information, see " <a href="#">Application Deployment Solution Monitoring</a> " on page 1309.
<b>Middleware Performance Monitors</b>	Measure statistics related to IBM WebSphere MQ during a scenario run. For more information, see " <a href="#">Middleware Performance Monitoring</a> " on page 1315
<b>Infrastructure Resources Monitor</b>	Displays information about network client data points during a scenario run using the Network Client graph. For more information, see " <a href="#">Infrastructure Resources Monitoring</a> " on page 1322.

The **J2EE & .NET Diagnostics Monitor** provides trace, time, and troubleshooting information for individual transactions through J2EE Web, application, and database servers. This monitor requires an additional installation, and is accessed from the **Diagnostics for J2EE/.NET** tab in the Controller.. For more information, contact your HP Sales representative.

## Add Machine Dialog Box

This dialog box enables you to add the machine that you want to monitor to the Monitored Server Machines list.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b> . In the dialog box that opens, click <b>Add</b> in the <b>Monitored Server Machines</b> section .
<b>Relevant tasks</b>	<a href="#">"How to Set Up a Monitoring Environment"</a> on page 1259

## Monitored Machine Information

User interface elements are described below:

UI Element	Description
Name	<p>The name or IP address of the machine that you want to monitor.</p> <ul style="list-style-type: none"><li>• <b>SNMP monitor:</b> If the SNMP agent is running on a different port than the default SNMP port, you need to define the port number using the format: &lt;server name&gt;:&lt;port number&gt;</li><li>• <b>MS IIS monitor:</b> To monitor an IIS server through a firewall, use TCP, port 139.</li></ul>
Platform	The operating system of the machine you want to monitor.

## SiteScope Server Information

For SiteScope server monitoring there are additional user interface elements:

**Note:** In order to connect to a SiteScope server with specific credentials, you must first stop the SiteScope monitor and remove all of its counters.

UI Element	Description
Name	The name of the SiteScope server.
Port	The SiteScope port. <b>Default:</b> 8888
Use Secure HTTP	Uses a secure HTTP connection to the SiteScope server.
Use Account	Instructs LoadRunner to use a specific SiteScope user account with the following account details: <ul style="list-style-type: none"><li>• <b>Account.</b> Internal SiteScope account name.</li><li>• <b>Username.</b> The display name of SiteScope account.</li><li>• <b>Password.</b> The password for the SiteScope account.</li></ul>

## <Monitor Type> Monitor Configuration Dialog Box

This dialog enables you to select the measurements to monitor during a scenario run.

To access	Right-click a graph > <b>Add Measurements</b> Click <b>Add</b> in the <b>Resource Measurements</b> section of <monitor name> dialog.
-----------	-----------------------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	<b>For DB2 monitors:</b> If there is no application working with a database, you can only monitor the database manager instance.
<b>Relevant tasks</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>

User interface elements are described below:

UI Element	Description
<b>Component/Counter Description</b>	Describes the selected component or counter.
<b>Host</b>	The name of the monitored machine.
<b>Measured Components</b>	A hierarchical view of the available components. Browse the tree and select the components you want to monitor. A description of the highlighted component appears in the <b>Component/Counter Description</b> box.
<b>Performance Counters</b>	Select the required performance counters. For details about the default monitor counters, see the relevant reference section for your monitor.


## *<monitor name>* Dialog Box

This dialog box enables you to add monitored server machines and access the dialogs to configure the measurements and data collection method.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b>
<b>Important information</b>	Before configuring a monitor's measurements, many servers require initial setup. The first step of <a href="#">"How to Set Up a Monitoring Environment" on page 1259</a> contains links to the setup instructions.
<b>Relevant tasks</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>

User interface elements are described below:

UI Element	Description
<b>Advanced</b>	Disabled.
<b>Description</b>	Displays a description of the selected resource measurement.
<b>Monitored Server Machines</b>	The machines whose resources are being monitored.  Displays the Add Machine dialog box, which adds the machine that you want to monitor to the existing list.  Removes the selected machine from the list.

UI Element	Description
<b>Resource Measurements on &lt;machine name&gt;</b>	Displays the resource measurements being monitored on the selected machine.  Displays the Resources dialog box that lets you create a list of resource measurements on the selected machine.  Removes the selected resource measurement from the list.

## Runtime and Transaction Monitoring

### Runtime Graphs Overview

The **Runtime** monitor provides information about the status of the Vusers participating in the scenario, and the number and types of errors that the Vusers generate. In addition, the Runtime monitor provides the User-Defined Data Points graph, which displays the real time values for user-defined points in a Vuser script.

The Runtime monitor is enabled by default—it automatically begins monitoring Vusers at the start of a scenario.

You can view the following Run-Time monitor graphs during a scenario run:

#### Running Vusers Graph

The monitor's **Running Vusers** graph provides information about the status of the Vusers running in the current scenario on all load generator machines. The graph shows the number of running Vusers, while the information in the legend indicates the number of Vusers in each state.

Color	Scale	Status	Max	Min	Avg	Std	Last
Green	1	Running	14	2	7.632653...	3.783389...	14
Red	1	Error	0	0	0	0	0
Yellow	1	Finished	0	0	0	0	0

The Status field of each Vuser displays the current status of the Vuser. The following table describes each Vuser status.

Status	Description
<b>Running</b>	The total number of Vusers currently running on all load generators.
<b>Ready</b>	The number of Vusers that completed the initialization section of the script and are ready to run.
<b>Finished</b>	The number of Vusers that have finished running. This includes both Vusers that passed and failed.
<b>Error</b>	The number of Vusers whose execution generated an error. Check the Status field in the Vuser view or the Output window for a complete explanation of the error.

#### User-Defined Data Points Graph

The **User-Defined Data Points** graph displays the real-time values of user-defined data points. You define a data point in your Vuser script by inserting an **lr\_user\_data\_point** function at the appropriate place (**user\_data\_point** for GUI Vusers and **lr.user\_data\_point** for Java Vusers).

```
Action1()
{
    lr_think_time(1);
    lr_user_data_point ("data_point_1",1);
    lr_user_data_point ("data_point_2",2);
    return 0;
}
```

For Vuser protocols that support the graphical script representations such as Web, you insert a data point as a user-defined step. Data point information is gathered each time the script executes the function or step. For more information about data points, see the Function Reference.

By default, LoadRunner displays all of the data points in a single graph. The legend provides information about each data point. If desired, you can hide specific data points using the legend below the graphs.

You can also view data points offline, after the completion of the scenario. For more information, see the *HP LoadRunner Analysis User Guide*.

#### Error Statistics Graph

The monitor's **Error Statistics** graph provides details about the number of errors that accrue during each second of the scenario run. The errors are grouped by error source—for example, the location in the script or the load generator name.

#### Vusers with Errors Graph

The **Vusers with Errors** graph provides details about the number of Vusers that generate errors during scenario execution. The errors are grouped by error source.

## **Transaction Monitor Graphs Overview**

The Transaction monitor displays the transaction rate and response time during a scenario run. The Transaction monitor is enabled by default—it automatically begins monitoring Vuser transactions at the start of a scenario run. To conserve resources, you can disable the Transaction monitor from the Controller.

You can view the following Transaction monitor graphs during a scenario run:

- The **Transaction Response Time** graph shows the average response time of transactions in seconds (y-axis) as a function of the elapsed time in the scenario (x-axis).
- The **Transactions per Second (Passed)** graph shows the number of successful transactions performed per second (y-axis) as a function of the elapsed time in the scenario (x-axis).
- The **Transactions per Second (Failed, Stopped)** graph shows the number of failed and

stopped transactions per second (y-axis) as a function of the elapsed time in the scenario (x-axis).

- The **Total Transactions per Second (Passed)** graph shows the total number of completed, successful transactions per second (y-axis) as a function of the elapsed time in the scenario (x-axis).

**Note:**

- If there are no transactions defined in your Vuser script or if no transactions are being executed, no data will be displayed in the online monitor graphs.
- To generate Web Page diagnostics for each transaction, configure the Diagnostics options from the Controller.

## Web Resource Monitors

### *Web Resource Monitoring Overview*

The Web Resource monitor enables you to analyze the following resources on the Web server during a scenario run: throughput, HTTP requests, downloaded pages, server retries, TCP/IP connections, and SSL Connections.

You can view the following resource monitor graphs during a scenario run:

#### **Hits per Second Graph**


The **Hits Per Second** graph shows the number of hits (HTTP requests) to the Web server (y-axis) as a function of the elapsed time in the scenario (x-axis). This graph can display the whole step, or the last 60, 180, 600, or 3600 seconds. You can compare this graph to the Transaction Response Time graph to see how the number of hits affects transaction performance.

#### **Throughput Graph**

The **Throughput** graph shows the amount of throughput (y-axis) on the Web server during each second of the scenario run (x-axis). Throughput is measured in bytes and represents the amount of data that the Vusers received from the server at any given second. You can compare this graph to the Transaction Response Time graph to see how the throughput affects transaction performance.

In the following example, the Transaction Response time graph is compared with the Throughput graph. It is apparent from the graph that as the throughput decreases, the transaction response time also decreases. The peak throughput occurred at approximately 1 minute into the step. The highest response time also occurred at this time.

**Example**



## HTTP Responses per Second Graph

The **HTTP Responses per Second** graph shows the number of HTTP status codes (y-axis)—which indicate the status of HTTP requests, for example, "the request was successful" or "the page was not found"—returned from the Web server during each second of the scenario run (x-axis).

The HTTP responses are grouped by status code. You can also group the results shown in this graph by script (using the "Group By" function) to locate scripts which generated error codes.

For a list of status codes and their explanations, see "[HTTP Status Codes](#)" on page 1286.

## WebSocket Statistics Graph

The **WebSocket Statistics** graph provides you with WebSocket statistics for your test run: the number of new connections, the number of bytes sent and received, and the number of failed connections.

For details, see "[WebSocket Statistics Monitor](#)" on page 1271.

## Pages Downloaded per Second Graph

The **Pages Downloaded per Second** graph shows the number of Web pages (y-axis) downloaded from the server during each second of the scenario run (x-axis). This graph helps you evaluate the amount of load Vusers generate, in terms of the number of pages downloaded.


**Note:** To view the Pages Downloaded per Second graph, you must select **Pages per second (HTML Mode only)** from the script's run-time settings Preferences tab before running your scenario.

Like throughput, downloaded pages per second is a representation of the amount of data that the Vusers received from the server at any given second.

- The Throughput graph takes into account each resource and its size (for example, the size of each .gif file, the size of each Web page).
- The Pages Downloaded per Second graph takes into account simply the number of pages.

In the following example, the Throughput graph is compared with the Pages Downloaded per Second graph. It is apparent from the graph that throughput is not proportional to the number of pages downloaded per second. For example, between 15 and 16 seconds into the scenario, the throughput decreased while the number of pages downloaded per second increased.

### Example



### Retries per Second Graph

The **Retries Per Second** graph shows the number of attempted Web server connections (y-axis) as a function of the elapsed time in the scenario (x-axis).

A server connection is retried when:

- The initial connection was unauthorized
- Proxy authentication is required
- The initial connection was closed by the server

- The initial connection to the server could not be made
- The server was initially unable to resolve the load generator's IP address

## Connections Graph

The **Connections** graph shows the number of open TCP/IP connections (y-axis) at each point in time of the scenario (x-axis). One HTML page may cause the browser to open several connections, when links on the page go to different Web addresses. Two connections are opened for each Web server.

This graph is useful in indicating when additional connections are needed. For example, if the number of connections reaches a plateau, and the transaction response time increases sharply, adding connections would probably cause a dramatic improvement in performance (reduction in the transaction response time).

## Connections per Second Graph

The **Connections Per Second** graph shows the number of new TCP/IP connections (y-axis) opened and the number of connections that are shut down each second of the scenario (x-axis).

This number should be a small fraction of the number of hits per second, because new TCP/IP connections are very expensive in terms of server, router and network resource consumption. Ideally, many HTTP requests should use the same connection, instead of opening a new connection for each request.

## SSLs per Second Graph

The **SSLs per Second** graph shows the number of new and reused SSL Connections (y-axis) opened in each second of the scenario (x-axis). An SSL connection is opened by the browser after a TCP/IP connection has been opened to a secure server.

Because creating a new SSL connection entails heavy resource consumption, you should try to open as few new SSL connections as possible; once you have established an SSL connection, you should reuse it. There should be no more than one new SSL connection per Vuser.

If you set your run-time settings to simulate a new Vuser at each iteration (using the run-time settings **Browser Emulation** node), you should have no more than one new SSL connection per Vuser per iteration. Ideally, you should have very few new TCP/IP and SSL connections each second.

## WebSocket Statistics Monitor


This **Web Resource** graph shows WebSocket statistics during the scenario run.

<b>Purpose</b>	Provides you with statistics for WebSocket connections, byte rate, and failed connections.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	WebSocket per second throughout the whole scenario.

<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
-------------	------------------------------------------------------------------------------------------------------------------------------------------------------------

### Example - WebSocket Statistics

In the following example, you can see that over 3000 bytes were sent per second.



The measurements for this monitor are:

- New Connections per second. This measurement shows an incrementation of one for each connection opened and a decrease of one for each connection closed
- Bytes Received per second
- Bytes Sent per second
- Failed Connections per second

## HTTP Status Codes

The following table displays a list of HTTP status codes. These codes appear in the ["Web Resource Monitoring Overview" on page 1268](#):

Code	Description	Code	Description
200	OK	406	Not Acceptable
201	Created	407	Proxy Authentication Required
202	Accepted	408	Request Timeout
203	Non-Authoritative Information	409	Conflict
204	No Content	410	Gone
205	Reset Content	411	Length Required

206	Partial Content	412	Precondition Failed
300	Multiple Choices	413	Request Entity Too Large
301	Moved Permanently	414	Request - URI Too Large
302	Found	415	Unsupported Media Type
303	See Other	416	Requested range not satisfiable
304	Not Modified	417	Expectation Failed
305	Use Proxy	500	Internal Server Error
307	Temporary Redirect	501	Not Implemented
400	Bad Request	502	Bad Gateway
401	Unauthorized	406	Not Acceptable
402	Payment Required	407	Proxy Authentication Required
403	Forbidden	503	Service Unavailable
404	Not Found	504	Gateway Timeout
405	Method Not Allowed	505	HTTP Version not supported

For more information on the status codes above, see  
<http://www.w3.org/Protocols/rfc2616/rfc2616-sec10.html#sec10>

## System Resource Monitoring

### ***System Resource Monitors Overview***

You use LoadRunner's System Resource monitors to monitor a machine's system resource usage during a scenario run and isolate server performance bottlenecks.

A primary factor in a transaction's response time is its system resource usage. Using the System Resource monitors, you can monitor the Windows, UNIX, and SNMP resources on a machine during a scenario run, and determine why a bottleneck occurred on a particular machine.

The resource monitors are automatically enabled when you execute a scenario. However, you must specify the machine you want to monitor and which resources to monitor for each machine. You can also add or remove machines and resources during the scenario run.

### ***Windows Resource Monitoring***

The Windows Resources monitor shows the Windows resources measured during the scenario run. Windows measurements correspond to the built-in counters available from the Windows Performance Monitor.

By default, LoadRunner monitors Windows resources using the native LoadRunner monitor engine.

If you are using the SiteScope monitor engine, ensure that SiteScope has been installed on a server. You can install SiteScope on the same server as the Controller, or on a dedicated server.

If you want to monitor a remote Windows server that does not use Windows domain security, you must authenticate the Controller on the remote Windows server. To authenticate the Controller, create an account, or change the password of the account used to log on to the Controller so that it matches the password and user name used to log on to the remote monitored Windows machine. When the remote Windows machine requests another machine's resources, it sends the logged-in user name and password of the machine requesting the resources.

Limited (non-admin) users cannot activate the monitoring using Windows Resource counters from a remote machine. This is due to a Windows limitation described in the following document: <http://support.microsoft.com/kb/300702>. You must log in with administrator permissions and verify that the Remote Registry service is running on the remote machine.

## **UNIX Resource Monitoring**

The UNIX Resources monitor shows the UNIX resources measured during the scenario. This graph helps you determine the impact of Vuser load on the various system resources.

The UNIX kernel statistics measurements include those available by the **rstatd** daemon. For a description of the measurements, see "[UNIX Resources Performance Counters](#)" on page 1276.

**Note:** You must configure an **rstatd** daemon on all Linux machines being monitored. For information, refer to the UNIX *man* pages, or see "[How to Set up the UNIX Monitoring Environment](#)" below.

## **SNMP Resource Monitoring**

The SNMP Resource monitor shows statistics for a Windows or UNIX machine using the Simple Network Management Protocol (SNMP). The SNMP Resources monitor is available for monitoring any machine that runs an SNMP agent, using the Simple Network Management Protocol (SNMP).

## **How to Set up the UNIX Monitoring Environment**

This task describes how to configure the UNIX environment before setting up the UNIX Resources monitor.

1. Verify whether the rstatd daemon is already configured

The rstatd daemon might already be configured, because when a machine receives an rstatd request, the inetd on that machine automatically activates the rstatd.

- The **rup** command reports various machine statistics, including rstatd configuration. Run the following command on the UNIX machine to view the machine statistics:

```
>rup host
```

- You can also use **lr\_host\_monitor** and see if it returns any relevant statistics.

If the command returns meaningful statistics, the rstatd daemon is already configured and activated. If not, or if you receive an error message, the rstatd daemon is not configured.

## 2. Configure the rstatd daemon

If the rstatd daemon is not yet configured, follow these steps to configure it:

- On the UNIX machine, run the command: **su root**
- Go to **/etc/inetd.conf** and look for the rstatd row (it begins with the word rstatd). If it is commented out (with a #), remove the comment directive, and save the file.
- From the command line, run:

```
kill -1 inet_pid
```

where `inet_pid` is the pid of the inetc process. This instructs the inetc to rescan the **/etc/inetd.conf** file and register all daemons which are uncommented, including the rstatd daemon.

- Run **rup** again.

If the command still does not indicate that the rstatd daemon is configured, contact your system administrator.

## 3. Configure the monitor for a UNIX machine over a firewall (optional)

To monitor a UNIX machine over a firewall, you must run a UNIX utility called **rpcinfo** and identify the rstatd's port number.

Run **rpcinfo -p <hostname>**. You will receive a list of all RPC servers registered in the host's portmapper, along with the port number. This list will not change until rstatd is stopped and rerun.

Some firewalls allow you to open an RPC program number instead of a port. In such cases, open program 100001. If prompted to include a version number, specify versions 3 and 4.

## 4. Configure the monitor measurements in the Controller

For task details, see "[How to Set Up a Monitoring Environment](#)" on page 1259.

In the **Resource Measurements on <machine>** section of the UNIX Resources dialog box, click **Add** to open the UNIX Kernel Statistics dialog box, and then select the available measurements and server properties.

For a description of the available UNIX monitor measurements, see "[UNIX Resources Performance Counters](#)" on the next page.

**Note:** In the Linux Kernel Statistics dialog box, selecting the **Recover Connection** check

box enables the Controller to try to recover a broken connection to a monitored Linux server. If the **Recover Connection** check box is not selected, a broken connection will be maintained until the end of the Controller session, and as a result server details will not be received from the monitored server. By default, the **Recover Connection** check box is selected.

## UNIX Resources Performance Counters

The following default measurements are available for the UNIX machine:

Measurement	Description
<b>Average load</b>	Average number of processes simultaneously in Ready state during the last minute
<b>Collision rate</b>	Collisions per second detected on the Ethernet
<b>Context switches rate</b>	Number of switches between processes or threads, per second
<b>CPU utilization</b>	Percent of time that the CPU is utilized
<b>Disk rate</b>	Rate of disk transfers
<b>Incoming packets error rate</b>	Errors per second while receiving Ethernet packets
<b>Incoming packets rate</b>	Incoming Ethernet packets per second
<b>Interrupt rate</b>	Number of device interrupts per second
<b>Outgoing packets errors rate</b>	Errors per second while sending Ethernet packets
<b>Outgoing packets rate</b>	Outgoing Ethernet packets per second
<b>Page-in rate</b>	Number of pages read to physical memory, per second
<b>Page-out rate</b>	Number of pages written to pagefile(s) and removed from physical memory, per second
<b>Paging rate</b>	Number of pages read to physical memory or written to pagefile(s), per second
<b>Swap-in rate</b>	Number of processes being swapped
<b>Swap-out rate</b>	Number of processes being swapped

<b>System mode CPU utilization</b>	Percent of time that the CPU is utilized in system mode
<b>User mode CPU utilization</b>	Percent of time CPU is utilized in user mode

**Note:** In the Linux Kernel Statistics dialog box, selecting the **Recover Connection** check box enables the Controller to try to recover a broken connection to a monitored Linux server. If the **Recover Connection** check box is not selected, a broken connection will be maintained until the end of the Controller session, and as a result server details will not be received from the monitored server. By default, the **Recover Connection** check box is selected.

## Add Windows Resources Measurements Dialog Box

This dialog box enables you to select the Windows resources to monitor. The Windows resources correspond to the built-in counters available from the Windows Performance Monitor.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b> In the <b>Resource Measurements</b> section of the <b>Windows Resources</b> dialog, click <b>Add</b> .
<b>Relevant tasks</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>

User interface elements are described below:

UI Element	Description
<b>Explain&gt;&gt;</b>	Displays a description of the selected counter.
<b>Counters/Measurements</b>	The resource counter/measurement to monitor. Select multiple counters using the CTRL key. For a list of available measurements, see <a href="#">Windows Resource Performance Counters</a> .
<b>Instances</b>	If multiple instances of the selected counter are running, select one or more instances to monitor for the selected counter.
<b>Object</b>	The object to monitor on the specified Windows machine.

## Network Delay Monitoring


### Network Monitoring Overview

Network configuration is a primary factor in the performance of applications. A poorly designed network can slow client activity to unacceptable levels.

You use Network monitoring to determine whether your network is causing a delay in the scenario. You can also determine the problematic network segment.

In a true Web or client/server system, there are many network segments. A single network segment with poor performance can affect the entire system.

The following diagram shows a typical network. To go from the server machine to the Vuser machine, data must travel over several segments.



The Network Delay Time monitor shows the delays for the complete path between the source and destination machines (for example the database server and Vuser host). The graph maps the delay as a function of the elapsed scenario time. Each defined path is represented by a separate line with a different color in the graph.

To measure network performance, the Network monitor sends packets of data across the network. When a packet returns, the monitor calculates the time it takes for the packet to go to the requested node and return. This time is the delay which appears in the Network Delay Time graph.

**Note:** The delays from the source machine to each of the nodes are measured concurrently, yet independently. It is therefore possible that the delay from the source machine to one of the nodes could be greater than the delay for the complete path between the source and destination machines.

## **How to Set Up the Network Monitoring Environment**

This task describes how to prepare your environment for network monitoring.

### **1. Prerequisites**

To enable network monitoring, you must install the LoadRunner agent on the source machine. You do not have to install the LoadRunner agent on the destination machine.

To run the Network monitor, you must have administrator privileges on the Windows source machine (unless you are using the ICMP protocol).

### **2. Configure the Linux source machine - optional**

You can run the Network monitor on Linux source machines, using UDP or ICMP. Before running the Network monitor from a Linux source machine, configure the source machine. For task details, see ["How to Configure the Linux Source Machine for Network Monitoring" on the next page](#).

### 3. Configure the firewall between the source and destination machines - Optional

If you are monitoring a network in which there are firewalls between the source and the destination machines, you must configure the firewalls to allow the network data packets to reach their destinations.

- If you are using the TCP protocol, the firewall that protects the destination machine should not block outgoing ICMP\_TIMEEXCEEDED packets (packets that are sent outside the firewall from the machine). In addition, the firewall protecting the source machine should allow ICMP\_TIMEEXCEEDED packets to enter, as well as TCP packets to exit.
- If you are using the ICMP protocol, the destination machine's firewall should not block incoming ICMP\_ECHO\_REQUEST packets, or outgoing ICMP\_ECHO\_REPLY and ICMP\_ECHO\_TIMEEXCEEDED packets. In addition, the firewall protecting the source machine should allow ICMP\_ECHO\_REPLY and ICMP\_ECHO\_TIMEEXCEEDED packets to enter, and ICMP\_ECHO\_REQUEST packets to exit.
- If you are using the UDP protocol, ensure that the UDP protocol can access the destination machine from the source machine. The destination machine's firewall should not block outgoing ICMP\_DEST\_UNREACHABLE and ICMP\_ECHO\_TIMEEXCEEDED packets. In addition, the firewall protecting the source machine should allow ICMP\_DEST\_UNREACHABLE and ICMP\_ECHO\_TIMEEXCEEDED packets to enter.

**Note:** To run the Network Delay monitor when there are firewalls between the Controller and the source machine, you must configure the LoadRunner agent, MI Listener, and Network Delay monitor for monitoring over a firewall.

### 4. Specify the network monitor paths

In the Controller Run tab graph tree view, select the **Network Delay Time** graph and drag it into the right pane. Right-click the graph and select **Add Measurements**. Define the paths using the following three dialog boxes:

- a. Add source and destinations machines. For details, see the ["Network Delay Time Dialog Box" on page 1282](#).
- b. Define the network monitor path. For details, see the ["Adding Destination Machines for Network Delay Monitoring Dialog Box" on page 1281](#).
- c. Configure the monitor settings for the defined path. For details, see the ["Network Monitor Settings for Defined Path Dialog Box" on page 1283](#).

## How to Configure the Linux Source Machine for Network Monitoring

This task describes how to configure a Linux source machine before running the network monitor.

### 1. Assign permissions where LoadRunner is installed locally.

Follow these steps to assign root permissions to the **merc\_webtrace** process:

- a. Log in to the source machine as root.
- b. Type: **cd <LoadRunner\_installation>/bin** to change to the **bin** folder.
- c. Type: **chown root merc\_webtrace** to make the root user the owner of the **merc\_webtrace** file.
- d. Type: **chmod +s merc\_webtrace** to add the s-bit to the file permissions.
- e. To verify, type **ls -l merc\_webtrace**. The permissions should look like this: **-rwsrwsr-x**.

### 2. Assign permissions where LoadRunner is installed on the network.

In a LoadRunner network installation, the **merc\_webtrace** process is on the network, not on the source machine disk. The following procedure copies the **merc\_webtrace** file to the local disk, configures **mdrv.dat** to recognize the process, and assigns root permissions to **merc\_webtrace**:

- a. Copy **merc\_webtrace** from **<LoadRunner\_installation>/bin** to anywhere on the local disk of the source machine. For example, to copy the file to the **/local/<LoadRunner>** folder, type: **cp /net/tools/LoadRunner\_installation/bin/merc\_webtrace /local/<LoadRunner>**

**Note:** All of the source machines that use the same network installation must copy **merc\_webtrace** to the identical folder path on their local disk (for example, **/local/<LoadRunner>**), since all of them use the same **mdrv.dat**.

- b. Add the following line to the **<LoadRunner\_installation>/dat/mdrv**. file, in the **[monitors\_server]** section:

**ExtCmdLine=-merc\_webtrace\_path /local/xxx**

- c. Log in to the source machine as root.
- d. Type: **cd LoadRunner\_installation/bin** to change to the **bin** folder.
- e. Type: **chown root merc\_webtrace** to make the root user the owner of the **merc\_webtrace** file.

- f. Type: chmod +s merc\_webtrace to add the s-bit to the file permissions.
- g. To verify, type ls -l merc\_webtrace. The permissions should look like:  
-rwsrwsr-x.

### 3. Connect to the Linux Source Machine through RSH

Follow these instructions if the Controller is connected to the source machine through RSH (default connection mode). In this case you do not need to activate the agent daemon.

Before running the Network monitor the first time, you enter an encrypted user name and password in the Network monitor configuration file.

- a. On the Windows taskbar, click **Start > All Programs > HP Software > HP LoadRunner > Tools > Password Encoder**. The Password Encoder window opens.
- b. In the **Password** box, type your RSH user name and password, separated by a vertical bar symbol. For example, myname|mypw.
- c. Click **Generate**. An encoded string is displayed in the Encoded string field.
- d. Click **Copy** to copy the encoded string to the clipboard.
- e. Add the following line to the <LoadRunner\_installation>/dat/monitors/ndm.cfg file, in the [hosts] section:

Host = <encrypted string copied from clipboard>

- f. Close and open the current scenario. LoadRunner will read the updated configuration file and recognize the source machine for monitoring.

### 4. Connect to the Linux Source Machine through the Agent

Follow these instructions for activating agent daemon on the source machine if the Controller is not connected to the source machine through RSH.

- a. Type m\_daemon\_setup -install from the <LoadRunner\_installation>/bin folder.
- b. Make sure that the agent daemon is running whenever you activate the Network monitor.
- c. To stop the Network Delay Monitor agent daemon, type m\_daemon\_setup -remove.



## ***Adding Destination Machines for Network Delay Monitoring Dialog Box***

This dialog box enables you to add destination machines for network delay monitoring, and configure additional network monitor settings.

<b>To access</b>	Network Delay Time dialog box > To machine(s) section> Click <b>Add</b>
------------------	-------------------------------------------------------------------------

<b>Important information</b>	The Network Delay Time Monitor cannot be configured to work in TCP mode on Windows XP SP2 or Vista.
<b>Relevant tasks</b>	<a href="#">"How to Set Up the Network Monitoring Environment" on page 1278</a>

User interface elements are described below:

UI Element	Description
 Add ...	Enter the name or URL of the machine at the final destination of the path you want to monitor in the New Machine Name dialog box. Repeat this for each path you want to monitor. <b>Note:</b> If the destination machine is <b>localhost</b> , enter the local machine's name and not <b>localhost</b> .
 Delete	Deletes the destination machine, to remove this path from the monitor graph.
 Rename	Renames the destination machine.
 Properties	Opens the Configuring Network Monitor Settings for Defined Path dialog box.
<b>From Machine</b>	Displays the name of the source machine.
<b>To Machines</b>	Displays the names or URLs of the destination machines.

## Network Delay Time Dialog Box

This dialog box enables you to select the network path you want to monitor.

<b>To access</b>	Right-click the Network Delay Time graph and select <b>Add Measurements</b> . This dialog appears only when you add measurements for the first time.
<b>Important information</b>	To run the Network monitor, you must have administrator privileges on the source machine (unless you are using the ICMP protocol).
<b>Relevant tasks</b>	<a href="#">"How to Set Up the Network Monitoring Environment" on page 1278</a>

User interface elements are described below:


UI Element	Description
------------	-------------

<b>Monitor the network delay from machine</b>	<p>Displays the name of the machine from which network monitoring begins (source machine).</p> <p>To add a machine, click <b>Add ...</b> and specify the server name or IP address and machine platform.</p> <p>Repeat this for each path you want to monitor.</p> <p><b>Important:</b> If there is a firewall between the Controller machine and the source machine, enter the server name or IP address of the source machine according to the following format:  <b>&lt;MI Listener machine&gt;:&lt;source machine local key&gt;</b>      where source machine local key is the Local Machine Key that you chose when configuring the LoadRunner agent on the source machine. (See "<a href="#">Agent Configuration Settings Dialog Box</a>" on page 1243)</p> <p><b>Example:</b> 12..12.3:vds</p>
<b>To machine(s)</b>	<p>Displays the network path in the format of <b>sourcemachine -&gt; destination machine</b>. To add a new destination machine, click <b>Add ...</b> and define the machine in the Adding Destination Machines for Network Delay Monitoring dialog box.</p>

## Network Delay Time Graph

The Network Delay Time graph shows the delay for the complete path between the source and destination machines (y-axis) as a function of the elapsed scenario time (x-axis).

Each path defined in the Add Destination Machines for Network Delay Monitoring dialog box is represented by a separate line with a different color in the graph.



## Network Monitor Settings for Defined Path Dialog Box

This dialog box enables you to set the network protocol, port, monitoring frequency, and monitoring packet retries.

<b>To access</b>	<b>Add Destination Machines for Network Delay Monitoring &gt; click Properties.</b>
<b>Relevant tasks</b>	<a href="#">"How to Set Up the Network Monitoring Environment" on page 1278</a>

User interface elements are described below:

UI Element	Description
<b>Monitor Settings</b>	<ul style="list-style-type: none"><li><b>Send request using X protocol.</b> Select the network protocol you want the monitor to use: TCP, UDP, or ICMP. It is recommended that you use the default protocol. The default in Windows is TCP, and in Linux is UDP.  When you use TCP or UDP protocols, administrator privileges are required on the source machine.</li><li><b>Send request to port.</b> Enter the port number to be used by the network path.</li><li><b>Enable display of network nodes by DNS names.</b> Enables you to view the DNS name of each node along the network path, in addition to its IP address.  Selecting this option will decrease the speed of the Network monitor.</li></ul>
<b>Monitoring Frequency</b>	<b>Send next packet X milliseconds after receipt of previous packet.</b> Select the number of milliseconds the monitor should wait between receiving a packet and sending out the next packet.  <b>Default:</b> 3000 milliseconds.  If you have a long, steady scenario, you can increase the interval by several seconds.
<b>Monitoring Packet Retries</b>	<ul style="list-style-type: none"><li><b>Wait X seconds for packet to return before retrying.</b> Select the maximum number of seconds that the monitor should wait for a packet to return before it retries to send the packet.  <b>Default:</b> 3 seconds.  If your network is very large and loaded (an internet connection with a low capacity), you should increase the value by several seconds. If you have a small network (such as a LAN), you can decrease the value.</li><li><b>Number of retries.</b> Select the number of times the monitor should try resending a packet to a node if the packet is not initially returned.  <b>Default:</b> 0.</li></ul>

## **Troubleshooting and Limitations - Network Delay Monitor**

This section describes troubleshooting for the Network Delay monitor.

If monitoring is unsuccessful and LoadRunner cannot locate the source or destination machines, make sure that the specified machines are available to your machine. Perform a "ping" operation. At the command line prompt, type:

```
ping server_name
```

To check the entire network path, use the trace route utility to verify that the path is valid.

For Windows, type tracert <server\_name>.

For Linux, type traceroute <server\_name>.

If the monitoring problem persists once you verify that the machines are accessible and that the network path is valid, perform the following procedures:

1. If you are using the TCP protocol, run <LoadRunner root folder>\bin\webtrace.exe from the source machine to determine whether the problem is related to the Controller, or the WebTrace technology on which the Network Delay monitor is based. If you are using the UDP or ICMP protocols, the problem must be related to the Controller and not WebTrace, since these protocols are not WebTrace technology-based.
2. If you receive results by running **webtrace.exe**, the problem is related to the Controller. Verify that the source machine is not a Linux machine, and contact the Customer Support Web site with the following information:
  - the Controller log file, **drv\_log.txt**, located in the **temp** folder of the Controller machine.
  - the **traceroute\_server** log file, located on the source machine.
  - the debug information located in the **TRS\_debug.txt** and **WT\_debug.txt** files in the path folder. These files are generated by adding the following line to the [monitors\_server] section of the <LoadRunner root folder>\dat\mdrv. file, and rerunning the Network monitor:

```
ExtCmdLine=-traceroute_debug path
```

3. If you do not receive results by running **webtrace.exe**, the problem is related to the WebTrace technology, on which the Network Delay monitor is based. Perform the following procedures on the source machine:
  - Verify that the **packet.sys** file (the Webtrace driver) exists in the **WINNT\system32\drivers** folder.
  - Check whether a driver (such as "Cloud" or "Sniffer") is installed on top of the network card driver. If so, remove it and run WebTrace again.
  - Verify that there are administrator permissions on the machine.
  - Using ipconfig /all, check that only one IP address is assigned to the network card. WebTrace does not know how to handle multiple IP addresses assigned to the same card (IP spoofing).
  - Check the number of network cards installed. Run webtrace -devlist to receive a list of the available network cards.

- If there is more than one card on the list, run `webtrace -dev <dev_name> <destination>`, where `<dev_name>` is one of the network card names shown in the list. If you discover that WebTrace is binding to the wrong card, you can use `webtrace set_device <dev_name>` to set a registry key that instructs WebTrace to use a specified card instead of the default one.
- Verify that the network card is of the Ethernet type.
- Contact the Customer Support Web site with the output of `webtrace.exe -debug` (for example, `webtrace.exe -debug www.merc-int.com`) and `ipconfig /all` on the machine.

## Web Server Resource Monitoring

### ***Web Server Resource Monitoring Overview***

Web Server Resource monitors provide you with information about the resource usage of the Microsoft IIS and Apache Web servers during performance test execution. To obtain this data, you need to activate the online monitor for the server and specify which resources you want to measure before executing the test.

**Note:** Certain measurements or counters are especially useful for determining server performance and isolating the cause of a bottleneck during an initial stress test on a Web server.

### ***How to change the Apache default server properties***

This task describes how to modify the Apache default server properties that are defined in the monitor configuration file.

1. Open the `apache.cfg` file in the `<performance center root folder>\dat\monitors` folder.
2. Edit the following parameters after the `Delimiter=:` statement:

**InfoURL.** Server statistics information URL

**ServerPort.** Server port number

**SamplingRate.** Rate (milliseconds) at which the LoadRunner monitor will poll the server for the statistics information. If this value is greater than 1000, LoadRunner will use it as its sampling rate. Otherwise, it will use the sampling rate defined in the Monitors tab of the Options dialog box.

3. Save and close the file.

## ***HTTP Status Codes***

The following table displays a list of HTTP status codes. These codes appear in the "Web Resource Monitoring Overview" on page 1268:

<b>Code</b>	<b>Description</b>	<b>Code</b>	<b>Description</b>
200	OK	406	Not Acceptable
201	Created	407	Proxy Authentication Required
202	Accepted	408	Request Timeout
203	Non-Authoritative Information	409	Conflict
204	No Content	410	Gone
205	Reset Content	411	Length Required
206	Partial Content	412	Precondition Failed
300	Multiple Choices	413	Request Entity Too Large
301	Moved Permanently	414	Request - URI Too Large
302	Found	415	Unsupported Media Type
303	See Other	416	Requested range not satisfiable
304	Not Modified	417	Expectation Failed
305	Use Proxy	500	Internal Server Error
307	Temporary Redirect	501	Not Implemented
400	Bad Request	502	Bad Gateway
401	Unauthorized	406	Not Acceptable
402	Payment Required	407	Proxy Authentication Required
403	Forbidden	503	Service Unavailable
404	Not Found	504	Gateway Timeout
405	Method Not Allowed	505	HTTP Version not supported

For more information on the status codes above, see  
<http://www.w3.org/Protocols/rfc2616/rfc2616-sec10.html#sec10>

## **Microsoft IIS Performance Counters**

The following table describes the measurements and server properties that can be monitored on the Microsoft IIS Web server during the test run:

<b>Object</b>	<b>Measurement</b>	<b>Description</b>
<b>Web Service</b>	<b>Bytes Sent/sec</b>	The rate at which the data bytes are sent by the Web service

<b>Web Service</b>	<b>Bytes Received/sec</b>	The rate at which the data bytes are received by the Web service
<b>Web Service</b>	<b>Get Requests/sec</b>	The rate at which HTTP requests using the GET method are made. Get requests are generally used for basic file retrievals or image maps, though they can be used with forms.
<b>Web Service</b>	<b>Post Requests/sec</b>	The rate at which HTTP requests using the POST method are made. Post requests are generally used for forms or gateway requests.
<b>Web Service</b>	<b>Maximum Connections</b>	The maximum number of simultaneous connections established with the Web service
<b>Web Service</b>	<b>Current Connections</b>	The current number of connections established with the Web service
<b>Web Service</b>	<b>Current NonAnonymous Users</b>	The number of users that currently have a non-anonymous connection using the Web service
<b>Web Service</b>	<b>Not Found Errors/sec</b>	The rate of errors due to requests that could not be satisfied by the server because the requested document could not be found. These are generally reported to the client as an HTTP 404 error code.
<b>Process</b>	<b>Private Bytes</b>	The current number of bytes that the process has allocated that cannot be shared with other processes.

## Apache Performance Counters

The following table describes the measurements and server properties that can be monitored on the Apache Web server during the test run:

<b>Measurement</b>	<b>Description</b>
<b># Busy Servers</b>	The number of servers in the Busy state
<b># Idle Servers</b>	The number of servers in the Idle state
<b>Apache CPU Usage</b>	The percentage of time the CPU is utilized by the Apache server
<b>Hits/sec</b>	The HTTP request rate
<b>KBytes Sent/sec</b>	The rate at which data bytes are sent from the Web server

# Web Application Server Monitoring

## ***Web Application Server Resource Monitoring Overview***

You use LoadRunner's Web Application Server Resource monitors to monitor Microsoft Active Server Pages during a scenario run and isolate application server performance bottlenecks.

- The Microsoft Active Server Pages (ASP) monitor displays statistics about the resource usage on the ASP server during the scenario run.

### ***MS Active Server Pages Performance Counters***

The following table describes the default counters that can be monitored:


Measurement	Description
<b>Errors per Second</b>	The number of errors per second.
<b>Requests Wait Time</b>	The number of milliseconds the most recent request was waiting in the queue.
<b>Requests Executing</b>	The number of requests currently executing.
<b>Requests Queued</b>	The number of requests waiting in the queue for service.
<b>Requests Rejected</b>	The total number of requests not executed because there were insufficient resources to process them.
<b>Requests Not Found</b>	The number of requests for files that were not found.
<b>Requests/sec</b>	The number of requests executed per second.
<b>Memory Allocated</b>	The total amount of memory, in bytes, currently allocated by Active Server Pages.
<b>Errors During Script Run-Time</b>	The number of failed requests due to run-time errors.
<b>Sessions Current</b>	The current number of sessions being serviced.
<b>Transactions/sec</b>	The number of transactions started per second.

## Microsoft Active Server Pages Dialog Box

This dialog box enables you to select the items to monitor on the MS Active Server Pages application server.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b> Click <b>Add</b> in the <b>Resource Measurements</b> section of <b>Microsoft Active Server Pages</b> dialog.
<b>Relevant tasks</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>
<b>See also</b>	<a href="#">"MS Active Server Pages Performance Counters" on the previous page</a>

User interface elements are described below:

UI Element	Description
 Add ...	Adds the selected measurement to the list of measurements in the <b>Measurements on &lt;machine&gt;</b> section of the Microsoft Active Server Pages dialog box.
<b>Counters</b>	Select a resource counter to monitor. Select multiple counters using the <b>CTRL</b> key. For a definition of each counter, click <b>Explain</b> .
<b>Instances</b>	If multiple instances of the selected counter are running, select one or more instances to monitor for the selected counter.
<b>Object</b>	Select the object being monitored on the specified machine.

## Database Server Resource Monitoring

### Database Resource Monitoring Overview

LoadRunner's Database Server Resource monitors measure database resource usage statistics for Oracle or SQL Servers during a scenario run. You use these monitors to isolate database server performance bottlenecks.

The SQL monitor can be configured as a native LoadRunner monitor, or as a SiteScope monitor.

There are two methods of monitoring Oracle database servers:

- The **Oracle native LoadRunner monitor** displays information from Oracle V\$ tables: Session statistics, V\$SESSTAT, system statistics, V\$SYSSTAT, and other table counters defined by the user in the custom query.
- The **SiteScope Oracle JDBC Monitor** monitors the server performance statistics from Oracle Database servers. You can monitor multiple parameters or counters with a single monitor instance. This allows you to watch server loading for performance, availability, and capacity

planning. You can create a separate Oracle JDBC Monitor instance for each Oracle database server in your environment.

Before defining the monitoring measurements for the Oracle monitor in the Controller, you must set up the monitoring environment on the database server:

**Note:** If there is no application working with a database, you can only monitor the database manager instance.

- For details about the Oracle monitor configuration, see "[How to Set Up the Oracle Monitoring Environment](#)" below.

You then enable each database resource monitor from the Controller by selecting the counters you want the monitor to measure.

## ***How to Set Up the Oracle Monitoring Environment***

This task describes how to set up the monitor environment before monitoring an Oracle database server using the native LoadRunner monitor.

**Note:** If a problem occurs in setting up the Oracle environment, check the Oracle server to view the error messages.

### **1. Prerequisites**

- Ensure that the Oracle client libraries are installed on the Controller machine.
- Verify that %OracleHome%\bin is included in the path environment variable. If it is not, add it.
- Ensure that the registries are updated for the version of Oracle that you are using and that they have the following key: HKEY\_LOCAL\_MACHINE\SOFTWARE\ORACLE
- Verify that the Oracle server you want to monitor is up and running. Note that it is possible to monitor several Oracle database servers concurrently.

**Note:** Only the 32-bit Oracle client should be installed on the Controller machine running the Oracle monitor. If you have a 16-bit and a 32-bit Oracle client installation on the Controller machine, the 16-bit installation should be uninstalled.


### **2. Configure the Oracle client/server connection**

Set the connection parameters so the Oracle client (Controller machine) can communicate with the Oracle server(s) you plan to monitor.

On the Controller machine, set the following configuration parameter either by editing the **tnsnames.ora** file in a text editor, or using the Oracle service configuration tool (for example, **Start > Programs > Oracle for Windows NT > Oracle Net8 Easy Config**):

- a new service name (TNS name) for the Oracle instance
- TCP protocol
- the host name (name of monitored server machine)
- the port number (usually 1521)
- the database SID (the default SID is ORCL)

For example:



```
tnsnames.ora
File Edit Search Help
TOPAZ.MERCURY.COM =
  (DESCRIPTION =
    (ADDRESS_LIST =
      (ADDRESS = (PROTOCOL = TCP)(HOST = night)(PORT = 1521))
    )
    (CONNECT_DATA =
      (SID = ORCL)
    )
  )
```

### 3. Connect to the monitored server machine and verify the connection

- a. Obtain a username and password for the service from your database administrator, and ensure that the Controller has database administrator privileges for the Oracle V\$ tables (**V\$SESSTAT**, **V\$SYSSTAT**, **V\$STATNAME**, **V\$instance**, **V\$SESSION**).
- b. Verify connection with the Oracle server by performing **tns ping** from the Controller machine.

**Note:** There may be a problem connecting if the Oracle server is behind a DMZ/firewall that limits its communication to application servers accessing it.

- c. Run SQL\*Plus from the Controller and attempt to log in to the Oracle server(s) with the desired username/password/server combination.
- d. Type **SELECT \* FROM V\$SYSSTAT** to verify that you can view the V\$SYSSTAT table on the Oracle server. Use similar queries to verify that you can view the V\$SESSTAT, V\$SESSION, V\$instance, V\$STATNAME, and V\$PROCESS tables on the server.

#### 4. Modify the monitoring sample rate (optional)

To change the length of each monitoring sample (in seconds), edit the `dat\monitors\vmmon.cfg` file in the LoadRunner root folder. The default rate is 10 seconds.

The minimum sampling rate for the Oracle Monitor is 10 seconds. If you set the sampling rate at less than 10 seconds, the Oracle Monitor will continue to monitor at 10 second intervals.

#### 5. Configure the Oracle monitor from the Controller

For task details (beginning with step 2), see "[How to Set Up a Monitoring Environment](#)" on [page 1259](#).

## Oracle Performance Counters

The following measurements are most commonly used when monitoring the Oracle server (from the V\$SYSSTAT table):

Measurement	Description
<b>CPU used by this session</b>	The amount of CPU time (in 10s of milliseconds) used by a session between the time a user call started and ended. Some user calls can be completed within 10 milliseconds and, as a result, the start and end-user call time can be the same. In this case, 0 milliseconds are added to the statistic. A similar problem can exist in the operating system reporting, especially on systems that suffer from many context switches.
<b>Bytes received via SQL*Net from client</b>	The total number of bytes received from the client over Net8.
<b>Logons current</b>	The total number of current logons
<b>Opens of replaced files</b>	The total number of files that needed to be reopened because they were no longer in the process file cache.
<b>User calls</b>	Oracle allocates resources (Call State Objects) to keep track of relevant user call data structures every time you log in, parse, or execute. When determining activity, the ratio of user calls to RPI calls gives you an indication of how much internal work is generated as a result of the type of requests the user is sending to Oracle.
<b>SQL*Net roundtrips to/from client</b>	The total number of Net8 messages sent to, and received from, the client.

<b>Bytes sent via SQL*Net to client</b>	The total number of bytes sent to the client from the foreground process(es).
<b>Opened cursors current</b>	The total number of current open cursors.
<b>DB block changes</b>	Closely related to consistent changes, this statistic counts the total number of changes that were made to all blocks in the SGA that were part of an update or delete operation. These are changes that generate redo log entries and hence will cause permanent changes to the database if the transaction is committed. This statistic is a rough indication of total database work and indicates (possibly on a per-transaction level) the rate at which buffers are being dirtied.
<b>Total file opens</b>	The total number of file opens being performed by the instance. Each process needs a number of files (control file, log file, database file) to work against the database.

## SQL Server Performance Counters

The following table describes the default counters that can be monitored on version 6.5 of the SQL Server:

Measurement	Description
<b>% Total Processor Time</b>	The average percentage of time that all the processors on the system are busy executing non-idle threads. On a multi-processor system, if all processors are always busy, this is 100%, if all processors are 50% busy this is 50% and if 1/4 of the processors are 100% busy this is 25%. It can be viewed as the fraction of the time spent doing useful work. Each processor is assigned an Idle thread in the Idle process which consumes those unproductive processor cycles not used by any other threads.
<b>% Processor Time</b>	The percentage of time that the processor is executing a non-idle thread. This counter was designed as a primary indicator of processor activity. It is calculated by measuring the time that the processor spends executing the thread of the idle process in each sample interval, and subtracting that value from 100%. (Each processor has an idle thread which consumes cycles when no other threads are ready to run). It can be viewed as the percentage of the sample interval spent doing useful work. This counter displays the average percentage of busy time observed during the sample interval. It is calculated by monitoring the time the service was inactive, and then subtracting that value from 100%.
<b>Cache Hit Ratio</b>	The percentage of time that a requested data page was found in the data cache (instead of being read from disk).

I/O - Batch Writes/sec	The number of 2K pages written to disk per second, using Batch I/O. The checkpoint thread is the primary user of Batch I/O.
I/O - Lazy Writes/sec	The number of 2K pages flushed to disk per second by the Lazy Writer.
I/O - Outstanding Reads	The number of physical reads pending.
I/O - Outstanding Writes	The number of physical writes pending.
I/O - Page Reads/sec	The number of physical page reads per second.
I/O - Transactions/sec	The number of Transact-SQL command batches executed per second.
User Connections	The number of open user connections.

## Configuring Oracle JDBC Monitor Dialog Box

This dialog box enables you to configure the connection parameters for the SiteScope Oracle JDBC monitor.

To access	Right-click the graph and select <b>Add Measurements</b> . This dialog appears only when you add measurements for the first time.
Relevant tasks	<a href="#">"How to Set Up the Oracle Monitoring Environment" on page 1291</a>
See also	<a href="#">"Oracle Performance Counters" on page 1293</a>

User interface elements are described below:

UI Element	Description
Instance	The database SID. <b>Example:</b> ORCL
Database Connection URL	The connection URL to the database you want to monitor. The URL should contain a database user name and password in the following format (including the colons and @ symbol): <b>jdbc:oracle:thin:@&lt;tcp addr&gt;:&lt;tcp port&gt;:&lt;db sid&gt;</b> <b>Example:</b> To connect to the ORCL database on a machine using port 1521 you would use <b>jdbc:oracle:thin:@206.168.191.19:1521:ORCL</b>

<b>Database User Name</b>	The user name that SiteScope should use to connect to the database. <b>Important:</b> You must have a valid Oracle user login that SiteScope will use to access the Oracle server for the Oracle JDBC Monitor. To verify that SiteScope will be able retrieve the Oracle database counters, sign in to the Oracle server with your user and try to execute the SQL statements found in the file: <b>SiteScope\templates.applications\commands.oraclejdbc</b>
<b>Database Password</b>	The password for the user name that SiteScope should use to connect to the database.
<b>Database Driver</b>	The driver used to connect to the database. Specify the Oracle Database Driver that was installed on the SiteScope server when setting up the monitor. <b>Example:</b> The Database Driver for the Oracle thin JDBC driver is: <b>oracle.jdbc.driver.OracleDriver</b>
<b>Connection Timeout</b>	An optional the time out value, in seconds, that SiteScope should to wait for a database connection to respond.
<b>Query Timeout</b>	An optional the time out value, in seconds, that SiteScope should to wait for a response from the database query. If the database does not respond within the period specified, SiteScope will report an error. <b>Note:</b> Some commonly used databases and database drivers do not support the Query Timeout feature. In these cases the Query Timeout value should be set to zero.
<b>Update every</b>	How often the monitor should read the server statistics. The default interval is to run or update the monitor once every 10 seconds. <b>Important:</b> The sum of the <b>Connection Timeout</b> value and <b>Query Timeout</b> value should always be less than the <b>Update every</b> value for the monitor.

## Shunra Network Virtualization Monitoring


### Average Latency Monitor

This graph shows the average recorded time required for a packet of data to travel from the indicated source point to the required destination, measured in milliseconds in the last 60 seconds.

<b>Purpose</b>	Helps you evaluate the time required for a packet of data to travel over the network.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The average latency—the time in milliseconds required for a packet of data to reach its destination, per 60 second intervals.
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>See also</b>	<a href="#">"Shunra Network Virtualization Monitoring" above</a>

### Example - Network Virtualization Per Group

In the following example, you can see that the latency for the **USA** group reached its peak at nearly 4 minutes into the scenario run, while the **Ukraine** group remained fairly constant at approximately 14 msec.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the "[Packet Loss Monitor](#)" below.

## Packet Loss Monitor


This graph shows packets lost during the last second of the scenario run. Packet loss occurs when data packets fail to reach their destination. It can result from gateway overload, signal degradation, channel congestion, or faulty hardware.

Purpose	Helps you understand how many data packets were lost over a specific time interval.
X-axis	Elapsed time since the start of the run.
Y-axis	<p>The following measurements:</p> <ul style="list-style-type: none"><li>The percentage of lost packets from all packets that were sent.</li><li>The number of data packets that were lost over 60 seconds.</li><li>The total number of packets that were lost.</li></ul>

<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>Tip</b>	<p>For LoadRunner Analysis (not applicable to monitoring graphs):</p> <p>To view information for a specific location:</p> <ol style="list-style-type: none"> <li>1. Click within the graph.</li> <li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li> <li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li> </ol>
<b>See also</b>	<a href="#">"Shunra Network Virtualization Monitoring" on page 1296</a>


### Example - Network Virtualization Per Group

The following example shows how the total of packet loss for the **USA** group increased as the scenario progressed.



### Example - Network Virtualization Per Load Generator

In the following example, you can see that the packet loss is grouped by load generator. This was the mode selected when you enabled Network Virtualization for the scenario.



### Average Throughput Monitor


This graph shows the average data traffic passing to or from the virtualized location, measured in kilobytes per second (kbps).

<b>Purpose</b>	Helps you evaluate the amount of load Vusers generate, in terms of the number of server and client throughput. The graph shows metrics for input and output traffic for both the server and client machines. Use the legend below the graph to determine the line color for each metric.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The rate of data passing to and from the virtual location, in kbps for the following metrics per group or load generator: <ul style="list-style-type: none"><li>• Input to the client machine</li><li>• Output from the client machine</li><li>• Input to the server machine</li><li>• Output from the server machine</li></ul>
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.

<b>Tips</b>	For LoadRunner Analysis (not applicable to monitoring graphs):  To view information for a specific location: <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<a href="#">"Total Throughput Monitor" on page 1302</a>

### Example

In the following example, the average server input throughput was the lowest for the **Ukraine** group.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the ["Packet Loss Monitor" on page 1297](#).


## Average Bandwidth Utilization Monitor

This graph shows the average bandwidth utilized by a virtual user or a virtualized location from the maximal available bandwidth allocated for it during the last second, measured in percentages.

<b>Purpose</b>	Helps you evaluate the bandwidth used over your network.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The percentage of bandwidth utilization.
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>Tips</b>	<p>For LoadRunner Analysis (not applicable to monitoring graphs):</p> <p>To view information for a specific location:</p> <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<a href="#">"Shunra Network Virtualization Monitoring" on page 1296</a>

### Example

In the following example, you can see that the bandwidth utilization for all locations and measurements, was constant at 10%.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the ["Packet Loss Monitor" on page 1297](#).

## Total Throughput Monitor


Displays the total data traffic passing to or from the virtualized location, measured in kilobytes.

<b>Purpose</b>	Helps you evaluate the total amount of load that Vusers generate while running a scenario with network virtualization.  The graph shows metrics for input and output traffic for both the server and client machines. The legend below the graph indicates the line color for each of these metrics.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Throughput of the server, in kilobytes per second (Kbps).
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the <b>General</b> tab of the Options dialog box.

<b>Tips</b>	For LoadRunner Analysis (not applicable to monitoring graphs):  To view information for a specific location: <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<a href="#">"Average Throughput Monitor" on page 1299</a>

### Example

In the following example, the highest throughput level was for the input data to the client, for the **Ukraine** group.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the ["Packet Loss Monitor" on page 1297](#).

## SiteScope Server Monitoring

## SiteScope Resource Monitoring

The SiteScope Resources monitor graph shows the SiteScope resources measured during the scenario run. The SiteScope monitor can measure server, network, and processor performance counters. For detailed information on the performance counters that SiteScope can monitor, refer to the relevant SiteScope documentation.

Before setting up the SiteScope monitor, ensure that SiteScope has been installed on a server. You can install SiteScope on the same machine as the Controller, or on a dedicated server. If SiteScope is installed on a machine other than the Controller, verify that the SiteScope machine is accessible from the Controller machine.

For details about monitoring, see "[How to Set Up a Monitoring Environment](#)" on page 1259

The information you need to provide for monitoring SiteScope machines differs slightly from other monitors. The enhanced integration lets you set up SiteScope monitoring on machines that require user authentication and Secure HTTP connections. For details, see the "[Add Machine Dialog Box](#)" on page 1263.

## Flex Monitoring

### Streaming Media Monitoring

#### ***Streaming Media Monitoring Overview***

To isolate server and client performance bottlenecks during a scenario run, you monitor the Windows Media Server and RealPlayer audio/video servers, as well as the RealPlayer and Media Player clients.

**Note:** For instructions on recording a script containing streaming media functions, see the HP Virtual User Generator.

The streaming media monitors provide you with performance information for the Windows Media Server and RealPlayer audio/video servers, as well as the RealPlayer and Media Player clients. To obtain data for the Windows Media Server and RealPlayer Server, you need to activate the streaming media monitor before executing the scenario, and indicate which statistics and measurements you want to monitor. The RealPlayer Client and Media Player Client do not require pre-session or scenario activation or configuration.

- The Real Client monitor graph shows statistics on the RealPlayer client machine as a function of the elapsed scenario time. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.
- The Media Player Client monitor graph shows statistics on the Windows Media Player client machine as a function of the elapsed scenario time. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.

## **RealPlayer Client Performance Counters**

The following table describes the RealPlayer Client measurements that are monitored:

<b>Measurement</b>	<b>Description</b>
<b>Current Bandwidth (Kbits/sec)</b>	The number of kilobytes in the last second
<b>Buffering Event Time (sec)</b>	The average time spent on buffering
<b>Network Performance</b>	The ratio (percentage) between the current bandwidth and the actual bandwidth of the clip
<b>Percentage of Recovered Packets</b>	The percentage of error packets that were recovered
<b>Percentage of Lost Packets</b>	The percentage of packets that were lost
<b>Percentage of Late Packets</b>	The percentage of late packets
<b>Time to First Frame Appearance (sec)</b>	The time for first frame appearance (measured from the start of the replay)
<b>Number of Buffering Events</b>	The average number of all buffering events
<b>Number of Buffering Seek Events</b>	The average number of buffering events resulting from a seek operation
<b>Buffering Seek Time</b>	The average time spent on buffering events resulting from a seek operation
<b>Number of Buffering Congestion Events</b>	The average number of buffering events resulting from network congestion
<b>Buffering Congestion Time</b>	The average time spent on buffering events resulting from network congestion
<b>Number of Buffering Live Pause Events</b>	The average number of buffering events resulting from live pause
<b>Buffering Live Pause Time</b>	The average time spent on buffering events resulting from live pause

## **Media Player Client Performance Counters**

The following table describes the Media Player Client measurements that are monitored:

<b>Measurement</b>	<b>Description</b>

<b>Average Buffering Events</b>	The number of times Media Player Client had to buffer incoming media data due to insufficient media content.
<b>Average Buffering Time (sec)</b>	The time spent by Media Player Client waiting for sufficient amount of media data in order to continue playing media clip.
<b>Current bandwidth (Kbits/sec)</b>	The number of kbits per second received.
<b>Number of Packets</b>	The number of packets sent by server for a particular media clip.
<b>Stream Interruptions</b>	The number of interruptions encountered by media player client while playing a media clip. This measurement includes the number of times Media Player Client had to buffer incoming media data, and any errors that occurred during playback.
<b>Stream Quality (Packet-level)</b>	The percentage ratio of packets received to total packets.
<b>Stream Quality (Sampling-level)</b>	The percentage of stream samples received on time (no delays in reception).
<b>Total number of recovered packets</b>	The number of lost packets that were recovered. This value is only relevant during network playback.
<b>Total number of lost packets</b>	The number of lost packets that were not recovered. This value is only relevant during network playback.

## ERP/CRM Server Resource Monitoring

### ***ERP/CRM Server Resource Monitoring Overview***

You use LoadRunner's ERP/CRM server resource monitors to monitor ERP/CRM servers during a scenario run and isolate server performance bottlenecks.

The Siebel Server Manager monitor displays statistics about the resource usage of a Siebel Server Manager during the scenario run.

### ***Siebel Server Manager Performance Counters***

The following table shows the default counters that can be measured:

Measurement	Description
<b>Average Connect Time</b>	The average connection time.
<b>Average Reply Size</b>	The average size of a user reply.
<b>Average Request Size</b>	The average size of a user request.
<b>Average Requests Per Session</b>	The average number of user requests per session.
<b>Average Response Time</b>	The average amount of time that it takes the server to respond to a request.
<b>Average Think Time</b>	The average amount of think time taken to respond to a request.
<b>Avg SQL Execute Time</b>	The average SQL execute time.
<b>Avg SQL Fetch Time</b>	The average SQL fetch time.
<b>Avg SQL Parse Time</b>	The average SQL parse time.
<b>CPU Time</b>	The CPU time used in the work process.
<b>Elapsed Time</b>	The total amount of elapsed time.
<b>Num of DBCConn Retries</b>	The number of database connection retries.
<b>Num of DLRbk Retries</b>	The number of DLRbk retries.
<b>Num of Exhausted Retries</b>	The total number of retries that expired.
<b>Number of SQL Executes</b>	The total number of SQL executes.
<b>Number of SQL Fetches</b>	The total number of SQL fetches.
<b>Number of SQL Parses</b>	The total number of SQL parses.
<b>Number of Sleeps</b>	The number of sleeps.
<b>Object Manager Errors</b>	The total number of object manager errors.
<b>Reply Messages</b>	The total number of reply messages.
<b>Request Messages</b>	The total number of request messages.
<b>SQL Execute Time</b>	The total SQL execute time.
<b>SQL Fetch Time</b>	The total SQL fetch time.
<b>SQL Parse Time</b>	The total SQL parse time.
<b>Sleep Time</b>	The total sleep time.
<b>Tests Attempted</b>	The number of tests attempted.

<b>Tests Failed</b>	The number of tests that failed.
<b>Tests Successful</b>	The number of tests that were successful.
<b>Total Reply Size</b>	The total reply size, measured in bytes.
<b>Total Request Size</b>	The total request size, measured in bytes.
<b>Total Response Time</b>	The total response time.
<b>Total Tasks</b>	The total number of tasks.
<b>Total Think Time</b>	The total think time.

## **Siebel Server Manager Configuration Dialog Box**

This dialog box allows you to select the Siebel Server Manager resources to monitor.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b> Click <b>Add</b> in the <b>Resource Measurements</b> section of Siebel Server Manager monitor dialog box.
<b>Relevant tasks</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>
<b>See also</b>	<a href="#">"Siebel Server Manager Performance Counters" on page 1306</a> <a href="#">"Troubleshooting and Limitations - Siebel Server Manager Monitor" below</a>

User interface elements are described below:

UI Element	Description
<b>Component/Counter Description</b>	Displays a description of the highlighted component.
<b>Host</b>	Displays the name of the monitored machine.
<b>Measured Components</b>	Displays the available components. Browse the tree and select the component you want to monitor.
<b>Performance Counters</b>	Displays the available counters for the selected component. Select the resource counter to monitor.

## **Troubleshooting and Limitations - Siebel Server Manager Monitor**

This section describes troubleshooting for the Siebel Server Manager Monitor

The Siebel Server Manager monitor uses a Siebel command line utility (srvrmgr) to gather its statistics. If you are having trouble getting the Siebel Server Manager monitor to work, run this command from the Siebel Server Manager client:

```
srvrmgr /s <server> /g <gateway> /e <enterprise> /u <user> /p <pw>
```

If this command works from the command line, but SiteScope has trouble executing the command, open **/sitescope/templates.applications/commandline.siebel**, and verify that you can run the following command from the command line:

```
CONNECT_COMMAND:$PATH$/srvrmgr /g $GATEWAY$ /e $ENTERPRISE$ /s $SERVERS$ /u  
$USERNAME$ /p $PASSWORD$
```

**Note:** On a Windows 2000 Advanced Server platform this command must be changed to:

```
CONNECT_COMMAND:$PATH$\srvrmgr.exe /g $GATEWAY$ /e $ENTERPRISE$ /s $SERVERS$  
/u $USERNAME$ /p $PASSWORD$
```

## Application Deployment Solution Monitoring

### ***Application Deployment Solution Monitoring Overview***

Using LoadRunner's Application Deployment Solution monitor, you can isolate server performance bottlenecks by monitoring the Citrix server during a scenario run.

LoadRunner's Citrix monitor provides you with information about the application deployment usage of the Citrix server during scenario execution. The Citrix monitor allows you to monitor the server performance statistics from Citrix servers. You can monitor multiple parameters (counters) with a single monitor instance. This allows you to watch server loading for performance, availability, and capacity planning.

To obtain performance data, you need to activate the online monitor for the server and specify which resources you want to measure before executing the scenario.

### ***How to Set up the Citrix Monitoring Environment***

This task describes the working order for setting up the monitoring environment.

#### **1. Prerequisites**

- Make sure that Citrix Server has been installed and is running.
- If Citrix Server machine is running Windows 2000, make sure that the server machine is also running the Remote Registry service.
- Make sure that the LoadRunner machine has administrator privileges to access the Citrix server.

- Measurements that monitor instances are valid for the currently running Citrix session only. If you run this test again, you will need to reconfigure the measurements that are instance-oriented.

To monitor the different instances, ensure that the server login and logout procedures are recorded in the **Vuser\_init** and **Vuser\_end** sections respectively, and not in the Action section of the script. For more information, see "["Vuser Script Sections" on page 255](#)".

## 2. Map the Network Drive

From the Controller machine, map a network drive to the Citrix server machine. This ensures that the required authentication is provided to the Controller to access the resource counters.

## 3. Launch PerfMon

Launch PerfMon from the Controller machine to enable the counters on the Citrix server. This allows you to monitor the same counters for the ICA Session object on the Citrix monitor.

## 4. Open the Connection with the Citrix Server

You can configure the Citrix monitor to view ICA Session object counters only if at least one session is being run on the Citrix server. If no "real" user has opened a connection with the Citrix server, you need to first initialize or run a Citrix Vuser against the server, and only then configure the Citrix Monitor and add the ICA Session counters. If you configure the Citrix monitor without first initializing or running a Citrix Vuser (or connecting to the Citrix server as a "real" user), you will not be able to view the ICA Session object.

## 5. Configure the Citrix monitor from the Controller

For task details, see "["How to Set Up a Monitoring Environment" on page 1259](#)".

# Citrix MetaFrame Performance Counters

The following sections describe some of the counters that can be measured.

## Non-Virtual Counters

The following table describes non-virtual counters:

Measurement	Description
% Disk Time	The percentage of elapsed time that the selected disk drive services read or write requests.

<b>% Processor Time</b>	The percentage of time that the processor executes a non-Idle thread. This counter is a primary indicator of processor activity. It is calculated by measuring the time that the processor spends executing the thread of the Idle process in each sample interval, and subtracting that value from 100%. (Each processor has an Idle thread which consumes cycles when no other threads are ready to run.) It can be viewed as the percentage of the sample interval spent doing useful work. This counter displays the average percentage of busy time observed during the sample interval. It is calculated by monitoring the time the service was inactive, and then subtracting that value from 100%.
<b>File data Operations/sec</b>	The rate that the computer issues Read and Write operations to file system devices. This does not include File Control Operations.
<b>Interrupts/sec</b>	The average number of hardware interrupts the processor receives and services per second. It does not include DPCs, which are counted separately. This value is an indirect indicator of the activity of devices that generate interrupts, such as the system clock, the mouse, disk drivers, data communication lines, network interface cards and other peripheral devices. These devices normally interrupt the processor when they have completed a task or require attention. Normal thread execution is suspended during interrupts. Most system clocks interrupt the processor every 10 milliseconds, creating a background of interrupt activity. This counter displays the difference between the values observed in the last two samples, divided by the duration of the sample interval.
<b>Output Session Line Speed</b>	This value represents the line speed from server to client for a session in bps.
<b>Input Session Line Speed</b>	This value represents the line speed from client to server for a session in bps.
<b>Page Faults/sec</b>	A count of the Page Faults in the processor. A page fault occurs when a process refers to a virtual memory page that is not in its Working Set in main memory. A Page Fault will not cause the page to be fetched from disk if that page is on the standby list, and hence already in main memory, or if it is in use by another process with whom the page is shared.
<b>Pages/sec</b>	The number of pages read from the disk or written to the disk to resolve memory references to pages that were not in memory at the time of the reference. This is the sum of Pages Input/sec and Pages Output/sec. This counter includes paging traffic on behalf of the system Cache to access file data for applications. This value also includes the pages to/from non-cached mapped memory files. This is the primary counter to observe if you are concerned about excessive memory pressure (that is, thrashing), and the excessive paging that may result.

<b>Pool Nonpaged Bytes</b>	The number of bytes in the Nonpaged Pool, a system memory area where space is acquired by operating system components as they accomplish their appointed tasks. Nonpaged Pool pages cannot be paged out to the paging file, but instead remain in main memory as long as they are allocated.
<b>Private Bytes</b>	The current number of bytes this process has allocated that cannot be shared with other processes.
<b>Processor Queue Length</b>	The instantaneous length of the processor queue in units of threads. This counter is always 0 unless you are also monitoring a thread counter. All processors use a single queue in which threads wait for processor cycles. This length does not include the threads that are currently executing. A sustained processor queue length greater than two generally indicates processor congestion. This is an instantaneous count, not an average over the time interval.
<b>Threads</b>	The number of threads in the computer at the time of data collection. Notice that this is an instantaneous count, not an average over the time interval. A thread is the basic executable entity that can execute instructions in a processor.
<b>Latency – Session Average</b>	This value represents the average client latency over the life of a session.
<b>Latency – Last Recorded</b>	This value represents the last recorded latency measurement for this session.
<b>Latency – Session Deviation</b>	This value represents the difference between the minimum and maximum measured values for a session.
<b>Input Session Bandwidth</b>	This value represents the bandwidth from client to server traffic for a session in bps.
<b>Input Session Compression</b>	This value represents the compression ratio for client to server traffic for a session.
<b>Output Session Bandwidth</b>	This value represents the bandwidth from server to client traffic for a session in bps.
<b>Output Session Compression</b>	This value represents the compression ratio for server to client traffic for a session.
<b>Output Session Linespeed</b>	This value represents the line speed from server to client for a session in bps.

## Virtual Channel Counters

The following table describes virtual channel counters:

Measurement	Description
<b>Input Audio Bandwidth</b>	This value represents the bandwidth from client to server traffic on the audio mapping channel. This is measured in bps.
<b>Input Clipboard Bandwidth</b>	This value represents the bandwidth from client to server traffic on the clipboard mapping channel. This is measured in bps.
<b>Input COM1 Bandwidth</b>	This value represents the bandwidth from client to server traffic on the COM1 channel. This is measured in bps.
<b>Input COM2 Bandwidth</b>	This value represents the bandwidth from client to server traffic on the COM2 channel. This is measured in bps.
<b>Input COM Bandwidth</b>	This value represents the bandwidth from client to server traffic on the COM channel. This is measured in bps.
<b>Input Control Channel Bandwidth</b>	This value represents the bandwidth from client to server traffic on the ICA control channel. This is measured in bps.
<b>Input Drive Bandwidth</b>	This value represents the bandwidth from client to server traffic on the client drive mapping channel. This is measured in bps.
<b>Input Font Data Bandwidth</b>	This value represents the bandwidth from client to server traffic on the local text echo font and keyboard layout channel. This is measured in bps.
<b>Input Licensing Bandwidth</b>	This value represents the bandwidth from server to client traffic on the licensing channel. This is measured in bps.
<b>Input LPT1 Bandwidth</b>	This value represents the bandwidth from client to server traffic on the LPT1 channel. This is measured in bps.
<b>Input LPT2 Bandwidth</b>	This value represents the bandwidth from client to server traffic on the LPT2 channel. This is measured in bps.
<b>Input Management Bandwidth</b>	This value represents the bandwidth from client to server traffic on the client management channel. This is measured in bps.
<b>Input PN Bandwidth</b>	This value represents the bandwidth from client to server traffic on the Program Neighborhood channel. This is measured in bps.
<b>Input Printer Bandwidth</b>	This value represents the bandwidth from client to server traffic on the printer spooler channel. This is measured in bps.
<b>Input Seamless Bandwidth</b>	This value represents the bandwidth from client to server traffic on the Seamless channel. This is measured in bps.

<b>Input Text Echo Bandwidth</b>	This value represents the bandwidth from client to server traffic on the local text echo data channel. This is measured in bps.
<b>Input Thinwire Bandwidth</b>	This value represents the bandwidth from client to server traffic on the Thinwire (graphics) channel. This is measured in bps.
<b>Input VideoFrame Bandwidth</b>	This value represents the bandwidth from client to server traffic on the VideoFrame channel. This is measured in bps.
<b>Output Audio Bandwidth</b>	This value represents the bandwidth from server to client traffic on the audio mapping channel. This is measured in bps.
<b>Output Clipboard Bandwidth</b>	This value represents the bandwidth from server to client traffic on the clipboard mapping channel. This is measured in bps.
<b>Output COM1 Bandwidth</b>	This value represents the bandwidth from server to client traffic on the COM1 channel. This is measured in bps.
<b>Output COM2 Bandwidth</b>	This value represents the bandwidth from server to client traffic on the COM2 channel. This is measured in bps.
<b>Output COM Bandwidth</b>	This value represents the bandwidth from server to client traffic on the COM channel. This is measured in bps.
<b>Output Control Channel Bandwidth</b>	This value represents the bandwidth from server to client traffic on the ICA control channel. This is measured in bps.
<b>Output Drive Bandwidth</b>	This value represents the bandwidth from server to client traffic on the client drive channel. This is measured in bps.
<b>Output Font Data Bandwidth</b>	This value represents the bandwidth from server to client traffic on the local text echo font and keyboard layout channel. This is measured in bps.
<b>Output Licensing Bandwidth</b>	This value represents the bandwidth from server to client traffic on the licensing channel. This is measured in bps.
<b>Output LPT1 Bandwidth</b>	This value represents the bandwidth from server to client traffic on the LPT1 channel. This is measured in bps.
<b>Output LPT2 Bandwidth</b>	This value represents the bandwidth from server to client traffic on the LPT2 channel. This is measured in bps.
<b>Output Management Bandwidth</b>	This value represents the bandwidth from server to client traffic on the client management channel. This is measured in bps.
<b>Output PN Bandwidth</b>	This value represents the bandwidth from server to client traffic on the Program Neighborhood channel. This is measured in bps.

<b>Output Printer Bandwidth</b>	This value represents the bandwidth from server to client traffic on the printer spooler channel. This is measured in bps.
<b>Output Seamless Bandwidth</b>	This value represents the bandwidth from server to client traffic on the Seamless channel. This is measured in bps.
<b>Output Text Echo Bandwidth</b>	This value represents the bandwidth from server to client traffic on the local text echo data channel. This is measured in bps.
<b>Output Thinwire Bandwidth</b>	This value represents the bandwidth from server to client traffic on the Thinwire (graphics) channel. This is measured in bps.
<b>Output VideoFrame Bandwidth</b>	This value represents the bandwidth from server to client traffic on the VideoFrame channel. This is measured in bps.

## Citrix Monitor Dialog Box

This dialog box enables you to configure the measurements for the Citrix monitor.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b> Click <b>Add</b> in the <b>Resource Measurements</b> section of <b>Citrix Monitor</b> dialog.
<b>Important information</b>	<b>Note:</b> For Citrix monitoring, if the dialog box freezes after clicking <b>Add</b> , you may need to rebuild the localhost cache on the Citrix server machine.
<b>Relevant tasks</b>	<a href="#">"How to Set up the Citrix Monitoring Environment" on page 1309</a>
<b>See also</b>	<a href="#">"How to Set Up a Monitoring Environment" on page 1259</a>

User interface elements are described below:

UI Element	Description
 <b>Add ...</b>	Adds the selected measurement to the list of measurements in the <b>Measurements on &lt;machine&gt;</b> section of the Citrix dialog box.
<b>Counters</b>	Select a resource counter to monitor. Select multiple counters using the CTRL key. For a definition of each counter, click <b>Explain</b> .
<b>Instances</b>	If multiple instances of the selected counter are running, select one or more instances to monitor for the selected counter.
<b>Object</b>	Select the object being monitored on the specified machine.

## Middleware Performance Monitoring

## **Middleware Performance Monitoring Overview**

A primary factor in a transaction's response time is the Middleware performance usage. LoadRunner's Middleware Performance monitors provide you with information about the Middleware performance usage of the IBM WebSphere MQ server during a scenario execution. To obtain performance data, you need to activate the online monitor for the server and specify which resources you want to measure before executing the scenario.

- The IBM WebSphere MQ monitor is used to monitor channel and queue performance counters on an IBM WebSphere MQ (version 5.x) Server.

## **How to Set Up the IBM WebSphere MQ Monitor**

This task describes how to configure the Controller and IBM WebSphere MQ machines:

### **1. Prerequisites**

Ensure that an IBM WebSphere MQ Client Connection (version 5.21 only) is installed on the Controller machine.

### **2. Configure the server environment to monitor events**

The LoadRunner MQ Monitor retrieves event messages from two standard MQSeries queues only:

- SYSTEM.ADMIN.PERFM.EVENT – performance events, such as "queue depth high"
- SYSTEM.ADMIN.CHANNEL.EVENT – channel events, such as "channel stopped"

Events must be enabled for the queue manager (and in many cases, on the applicable object, as well). Performance events are enabled by setting attributes for the queue on the MQ Server. Channel events are enabled by default, and cannot be disabled.

**Note:** The IBM WebSphere MQ monitor does not retrieve data from a queue manager after the queue manager has been restarted.

- a. Run the following MQSC command:  
ALTER QMGR PERMEN(ENABLED).

- b. Set the queue attributes. For a list of queue attributes, "[IBM WebSphere MQ Queue Attributes](#)" on page 1319.

### **3. Add the monitored server to the Controller**

- a. In the Controller Run view, click the IBM WebSphere MQ graph in the graph tree, and drag

it into the right pane.

- b. Right-click the graph and select **Add Measurements**, or click anywhere on the graph and select **Monitors > Add Measurements**. The IBM WebSphere MQ dialog box opens.

In the **Monitored Server Machines** section, click **Add**. The Add Machine dialog box opens.

- c. The first time that you add measurements, enter the server name or IP address of the machine you want to monitor. The format of the server name is <machine name>:<port number>. Select the platform on which the machine runs, and click **OK**.
  - d. In the **Resource Measurements** section of the IBM WebSphere MQ dialog box, click **Add**.
4. Configure the IBM WebSphere MQ monitor

The IBM WebSphere MQ monitor connects to the IBM WebSphere MQ server (via the MQ Client Connection installed on the Controller machine). In MQ Client environments, the client machine connects to an MQ Server instance, and uses the Server's resources as if they were local to the client machine.

- Specify the connection information and measurements in the MQ Monitor Add Measurements dialog.

## ***IBM WebSphere MQ Performance Counters***

The following tables list the available IBM WebSphere MQ monitor measurements:

### **Queue Performance Counters**

The following table describes the Queue Performance counters:

Measurement	Description
<b>Event - Queue Depth High (events per second)</b>	An event triggered when the queue depth reaches the configured maximum depth.
<b>Event - Queue Depth Low (events per second)</b>	An event triggered when the queue depth reaches the configured minimum depth.
<b>Event - Queue Full (events per second)</b>	An event triggered when an attempt is made to put a message on a queue that is full.
<b>Event - Queue Service Interval High (events per second)</b>	An event triggered when no messages are put to or retrieved from a queue within the timeout threshold.

<b>Event - Queue Service Interval OK (events per second)</b>	An event triggered when a message has been put to or retrieved from a queue within the timeout threshold.
<b>Status - Current Depth</b>	Current count of messages on a local queue. This measurement applies only to local queues of the monitored queue manager.
<b>Status - Open Input Count</b>	Current count of open input handles. Input handles are opened so that an application may "put" messages to a queue.
<b>Status - Open Output Count</b>	Current count of open output handles. Output handles are opened so that an application may "get" messages from a queue.

## Channel Performance Counters

The following table describes the Channel Performance counters:

Measurement	Description
<b>Event - Channel Activated (events per second)</b>	Event generated when a channel, waiting to become active but inhibited from doing so due to a shortage of queue manager channel slots, becomes active due to the sudden availability of a channel slot.
<b>Event - Channel Not Activated (events per second)</b>	Event generated when a channel, attempts to become active but inhibited from doing so due to a shortage of queue manager channel slots.
<b>Event - Channel Started (events per second)</b>	Event generated when a channel is started.
<b>Event - Channel Stopped (events per second)</b>	Event generated when a channel is stopped, regardless of source of stoppage.
<b>Event - Channel Stopped by User (events per second)</b>	Event generated when a channel is stopped by a user.

<b>Status - Channel State</b>	The current state of a channel. Channels pass through several states from stopped (inactive state) to running (fully active state). Channel states range from 0 (stopped) to 6 (running).
<b>Status - Messages Transferred</b>	The count of messages that have been sent over the channel. If no traffic is occurring over the channel, this measurement will be zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Buffer Received</b>	The count of buffers that have been received over the channel. If no traffic is occurring over the channel, this measurement will be zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Buffer Sent</b>	The count of buffers that have been sent over the channel. If no traffic is occurring over the channel, this measurement will be zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Bytes Received</b>	The count of bytes that have been received over the channel. If no traffic is occurring over the channel, this measurement will appear as zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Bytes Sent</b>	The count of bytes that have been sent over the channel. If no traffic is occurring over the channel, this measurement will appear as zero. If the channel has not been started since the queue manager was started, no measurement will be available.

## IBM WebSphere MQ Queue Attributes

You set the following queue attributes using the MQSC command ALTER QMGR PERFMEV (ENABLED) :

Measurement	Set Event Attributes
<b>Event - Queue Depth High</b>	<ul style="list-style-type: none"> <li><b>QDEPTHHI(integer)</b> - where integer is a value expressed as a percentage of maximum messages allowed, and is in the range of 0 to 100 inclusive.</li> <li><b>QDPHIEV(action)</b> - where action is the word "ENABLED" or "DISABLED", enabling or disabling the generation of the event, respectively.</li> </ul>

<b>Event - Queue Depth Low</b>	To enable the event for a queue, the following attributes of the queue must be set: <ul style="list-style-type: none"><li>• <b>QDEPTHLO(integer)</b> - where integer is a value expressed as a percentage of maximum messages allowed, and is in the range of 0 to 100 inclusive.</li><li>• <b>QDPLOEV(action)</b> - where action is the word "ENABLED" or "DISABLED", enabling or disabling the generation of the event, respectively.</li></ul>
<b>Event - Queue Full</b>	<ul style="list-style-type: none"><li>• <b>QDEPTHHI(integer)</b> – where integer is a value expressed as a percentage of maximum messages allowed, and is in the range of 0 to 100 inclusive.</li><li>• <b>QDPMAXEV(action)</b> – where action is the word "ENABLED" or "DISABLED", enabling or disabling the generation of the event, respectively.</li></ul>
<b>Event - Queue Service Interval High</b>	<ul style="list-style-type: none"><li>• <b>QSVCINT(integer)</b> – where integer is a value expressed as milliseconds, in the range of 0 and 999,,999, inclusive. Note: this value is shared with Queue Service Interval OK.</li><li>• <b>QSVCIEV(type)</b> – where type is the word "HIGH", "OK", or "NONE", enabling service interval high events, enabling service interval ok events, or disabling the generation of the event, respectively.</li></ul>
<b>Event - Queue Service Interval OK</b>	<ul style="list-style-type: none"><li>• <b>QSVCINT(integer)</b> – where integer is a value expressed as milliseconds, in the range of 0 and 999,999,999, inclusive. Note: this value is shared with Queue Service Interval High.</li><li>• <b>QSVCIEV(type)</b> – where type is the word "HIGH", "OK", or "NONE", enabling service interval high events, enabling service interval ok events, or disabling the generation of the event, respectively.</li></ul>

## MQ Monitor Add Measurements Dialog Box

This dialog box enables you to configure the monitor by choosing which measurements to monitor on the machine.

<b>To access</b>	Right-click a graph > <b>Add Measurements</b> Click <b>Add</b> in the <b>Resource Measurements</b> section of the <b>IBM WebSphere MQ</b> dialog.
<b>Important information</b>	User entries for any text box are limited to 48 characters.
<b>Relevant tasks</b>	<a href="#">"How to Set Up the IBM WebSphere MQ Monitor" on page 1316</a>
<b>See also</b>	<a href="#">"IBM WebSphere MQ Performance Counters" on page 1317</a>

User interface elements are described below:

UI Element	Description
<b>Alternate Queue</b>	<p>If the event configured for monitoring is from a remote queue manager (other than the one identified in the queue manager field of the IBM WebSphere MQ Add Measurements dialog box), click <b>Alternate Queue</b> to enter the name of an alternate queue manager.</p> <p><b>Note:</b> When you add an alternate queue manager, this becomes the default queue manager for any events that you subsequently add. To return to the queue manager to which you are connected, enter that name in the Alternate Queue Manager dialog box.</p>
<b>Available Measurements</b>	<p><b>Object Type.</b> Select an object type from either Channel or Queue.</p> <p><b>Object Name.</b> Enter a name for object you want to monitor.</p> <p><b>Event/Attribute.</b> Select the events and attributes you want to monitor for the selected object.</p> <p><b>Filter System Objects.</b> Select to enable the system objects filter.</p> <p><b>Add Object.</b> Enables you to add a new object name to the Object name list.</p> <p><b>Add.</b> Enables you to add an Event or Attribute to an object.</p> <p><b>Remove.</b> Enables you to remove a monitored object event or attribute from the Object name list.</p> <p><b>Alternate Queue.</b> Enter the name of an alternate queue manager if the event is from a remote queue manager.</p>
<b>Connections Information</b>	<p><b>Server.</b> The name of the server you are monitoring.</p> <p><b>Client Channel.</b> Enter the name of the channel through which a client connection is made to an MQ Server.</p> <ul style="list-style-type: none"> <li>• <b>Note:</b> You can set up a specific channel on an MQ Server instance, or use the default "SYSTEM.DEF.SVRCONN" channel. If the client channel is undefined, the MQ Server will be inaccessible via client connections (the MQ Monitor will not work, as it will not be able to connect to the queue manager which it is supposed to monitor).</li> </ul> <p><b>Queue Manager.</b> Enter the name of the queue manager to be monitored.</p> <ul style="list-style-type: none"> <li>• <b>Note:</b> The monitor is not restricted to monitoring only the queue manager to which it is connected. You can configure multiple queue managers to write to the event queue of a central queue manager for centralized monitoring (this applies to Events only, not polled object attributes). All events contain a queue manager attribute identifying their source.</li> <li>• <b>Note:</b> A queue manager can only be accessed by one Controller or monitoring application at any one time.</li> </ul>
<b>Filter system objects</b>	<p>By default, only user-defined objects are displayed in the <b>Object name</b> list. To show all objects, clear the <b>Filter System Objects</b> check box. You can modify the filter settings, in the &lt;LoadRunner_installation&gt;\dat\monitors\mqseries.cfg file.</p>
<b>Monitored Object list</b>	<p>A list of monitored objects, including the object's name, events and attributes, and alternate queue manager.</p>

# Infrastructure Resources Monitoring

## ***Infrastructure Resources Monitoring Overview***

Using LoadRunner's Network Client monitor, you can monitor network client resources for FTP, POP3, SMTP, IMAP, and DNS Vusers during a scenario run and isolate client performance bottlenecks.

### **Activating the Network Client Monitor**

The Network Client online monitor graph is only available during scenarios that run relevant scripts, such as FTP, POP3, and so forth.

You can view this graph by dragging it from the Infrastructure Resources Graph section in the graph tree into the right pane of the Run view. The graph appears in the graph view area.

## ***Network Client Performance Counters***

The following table describes the Network Client measurements that are monitored:

Measurement	Description
<b>Pings per sec</b>	Number of pings per second
<b>Data transfer bytes per sec</b>	Number of data bytes transferred per second
<b>Data receive bytes per sec</b>	Number of data bytes received per second
<b>Connections per sec</b>	Number of connections per second
<b>Accept connections per sec</b>	Number of connections accepted per seconds
<b>SSL Connections per sec</b>	Number of SSL connections per second
<b>SSL Data transfer bytes per sec</b>	Number of SSL data bytes transferred per second
<b>SSL Data receive bytes per sec</b>	Number of SSL data bytes received per second
<b>SSL Accept connections per sec</b>	Number of SSL connections accepted per seconds

# Service Virtualization Integration

## **HP Service Virtualization Integration - Overview**

Some business processes contain services that are not available. For example, your business process might include a service that is in development or incurs a cost, such as processing a credit card through a third-party vendor. To facilitate load testing these business processes, LoadRunner Controller integrates with HP Service Virtualization. This integration allows you to run virtual services that simulate actual services. By using a virtual service, you can load test and replace


actual services with a simulated services that mirror both the **data model**<sup>1</sup> and the **performance model**<sup>2</sup>.

For details on creating virtualized services, see the ***HP Service Virtualization User Guide***.

The workflow below explains how HP Service Virtualization integrates with LoadRunner processes:

<sup>1</sup>Definition of the data that is sent by the service to the server and the expected response. You can define several data models for one service.

<sup>2</sup>Definition of the expected performance, such as reponse time, of the service.



For details, see

["How to Use Service Virtualization when Designing Scenarios" on page 1327](#)

["Service Virtualization Monitoring Overview" below](#)

[" Service Virtualization User Interface" on page 1329](#)

## **Virtual Service Locks**

When your scenario contains virtualized services, these services are automatically locked and cannot be used by other users while the scenario is running. Virtualized services may be locked by you or other users for editing, simulation, or deployment.

- If your scenario includes a service that has been locked by another user, start run will fail and an error message appears in the output window.
- If your scenario is running and you update the scenario to include a service that has been locked by another user, the scenario continues running; however, an error message appears in the output window.

## **Service Virtualization Monitoring Overview**

The HP Service Virtualization monitors enable you to analyze the status and performance of the simulated services during the load test run.

For example, you may integrate a payment process service containing the following services and operations into your script:

Type	Example Name	Example Description
Service	CreditServ	Process online credit card payments
Operation	CreditServ.PurchaseRequest	Cardholder requests product/service
Operation	CreditServ.AuthorizationRequest	Merchant request authorization for payment
Operation	CreditServ.AuthorizationApproval	Credit card company authorizes or denies payment

The online monitors measure the overall behavior of the service and each operation. The following flowchart illustrates using a service and operations for credit card payment.



Monitor	Measurements	Description
Operations	Average Response Time	Average response time of virtual service in milliseconds.
	Hit Rate	Number of requests per second of the virtual service operation.
	Throughput	Data sent and received by virtual service operation measured in megabytes.

Monitor	Measurements	Description
Services	Average Response Time	Average response time of virtual service in milliseconds.
	Data Simulation Accuracy	Accuracy of data model emulation on virtual service, displayed as a percentage.
	Hit Rate	The number of requests per second of the virtual service.
	Performance Simulation Accuracy	Accuracy of performance model emulation on virtual service, displayed as a percentage.
	Throughput	Data sent and received on virtual service measured in megabytes.

## How to Use Service Virtualization when Designing Scenarios

As part of your load test, you may want to test services which are a part of your business scenario. Instead of loading actual services, you can use simulated services in your test run. The virtualized services are a simulation of actual services.

Using simulated services in your test is helpful if using actual services involves an additional cost or requires the service of an application that is under development or inaccessible at the time when you run your scenario test.

When designing a goal-oriented scenario, you can load virtual services to run with your load test. You can open the **Service Virtualization** dialog box from the Design tab of a Manual or Goal-Oriented Scenario. The task describes how to load services to your test run.

In the task "[How to Design a Manual Scenario](#)" on page 1045, after the step, *Define a schedule for the scenario*,

or

In the task "[How to Design a Goal-Oriented Scenario](#)" on page 1043, after the step, *Assign each script a percentage of the total scenario target*,

do the following:

### Prerequisites

- If your script requires the service to be running while you record your business process, open HP Service Virtualization simultaneously and deploy the virtualized service. Record the script as usual.
- There are two scenarios in which you may want to instruct your application to use a virtual service in place of the actual service:

1. Application components that use the service are embedded in the code or in a configuration file. In this case, you will need to update the code in your application or update the configuration file to point to the new URL.

Examples:

A .NET Desktop application uses a web service, and the url is set using a constant:  
`stringURL = http://hp.com`

Service or back-end component uses the web service and the URL is configured in the app.config file.

2. The service is consumed by accessing UDDI or other registry component(Systinet) and the URL is retrieved at run-time . In this case, you will need to update the end point URL in UDDI/Systinet.

## Create a Load Test in Controller

1. In the **Design** tab, click the **Service Virtualization** button .
2. In the **Service Virtualization** dialog box click **Add Project**.
3. In the **Add Project** dialog box, search and select for the relevant project containing the simulated services you want to run with your load test.
4. Click the **Simulate** check box of the service you want to run.
5. For each selected service, select the relevant **Data model** and **Performance model** to associate with the virtual service. In the "[How to Use Service Virtualization when Designing Scenarios](#)" on the previous page, we used credit card processing as an example of a virtual service. In this case, possible data models could be the requests and responses for Visa, MasterCard or PayPal and possible performance models could be peak and slow.
6. In the **Simulation Server** cell for the selected service, verify that the address of the simulation server is correct. If necessary, you can change the address of the simulation server.
7. Click the **Check Deployment** button to load the services. One of the following statuses are displayed:
  - Green  - indicates the service is deployed
  - Red  - indicates the service is not deployed

**Note.** The virtual service must be loaded on the simulation server to be able to deploy the service as part of your load test in Controller.
8. Optional - Select **Set all simulated services to standby -ignore all calls to all simulated services** to ignore all of the Performance model and Data model settings configured for each service.

## Run a Load Test In Controller

You can stop, start, or load a new project during your load test run.

The following task describes how to update services during your load test run.

1. In the **Run** tab, in the **Scenario Status** pane, click the status (ON or OFF). link for the Service Virtualization to open the Service Virtualization dialog box.
2. In the **Service Virtualization** dialog box, select the **Simulate** check box of the service you want to stop or start.
3. Click **Add Project** to load the project containing the virutalized services to run with your load test.


**Note:** If you are using a service that can be accessed by other machines, the service is locked until it is not deployed on the machine on which you are running the load test.

## View Online Monitors

For details, see "[Service Virtualization Monitoring Overview](#)" on page 1325

# Service Virtualization User Interface

The Service Virtualization user interface provides integration with HP Service Virtualization designer. This integration allows you to test services with virtualized servers instead of real-time services..



<b>To access</b>	Click the Virtualized Service Settings button  from the Controller toolbar.
<b>Relevant tasks</b>	<a href="#">"How to Use Service Virtualization when Designing Scenarios" on page 1327</a>

User interface elements are described below(unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Set all simulated services to standby -ignore all calls to all simulated services.</b>	Ignores calls to the virtual services.
<b>Add Project</b>	Opens the Add Project dialog box, enabling you to specify or browse for an HP Service Virtualization project. Project files have a .vproj extension.
<b>Delete Project</b>	Remove the selected project from the list of virtualized services.
<b>Refresh Project</b>	Reload the project from its source location.
<b>Deploy Project</b>	Start all services contained in the project.
<b>Check Deployment</b>	Checks if the virtual service was deployed (started) on the virtualization server.
<b>Servers Security</b>	Specify user credentials for each Service Virtualization server.

<Virtualization services>	<p>Lists the virtualized services displaying the following information:</p> <ul style="list-style-type: none"><li>• <b>Simulate.</b> A check box indicating if the virtual service will be included in the test.</li><li>• <b>Project Name.</b> The name of the HP Service Virtualization project containing the virtual service.</li><li>• <b>Service Name.</b> The name of the virtual service to use during test execution.</li><li>• <b>Data Model.</b> The defined set of data sent from the client (request) to the application server and the expected data sent back to the client (response).</li><li>• <b>Performance Model.</b> The model that defines how fast the response and request are processed.</li><li>• <b>Emulation Server.</b> The machine used for emulating the virtual service. If the value was configured on the server machine as localhost, make sure to change it to the actual server name.</li><li>• <b>Deployed.</b> An indicator showing the deployment status:<ul style="list-style-type: none"><li>▪ <b>Unknown Status.</b> Click <b>Check Deployment</b> to check the status.</li><li>▪ <b>Deployed.</b> Successfully deployed.</li><li>▪ <b>Not Deployed.</b> The service is not deployed on the specified emulation server.</li></ul></li></ul>
---------------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------


## Appendices

### Secure Host Communication

#### Secure Host Communication Overview

The need to secure communication channels from hackers attacking the corporate networks is critical. Securing communication channels ensures confidentiality, integrity, and the user's authenticity within the scope of the load testing application.

Secure communication is established between the Controller and load generator hosts using a **security key**. Each host in the system must be set up with the identical security key. If security keys on the hosts do not match, secure communication cannot be established.



A host is in **secure mode** when it has a security key and security is enforced.

A host is in **non-secure mode**:

- If it has no security key
- If it has a security key but security is **not** enforced

When a host in secure mode tries to communicate with a host in non-secure mode, security is automatically enforced on the non-secure host—assuming their security keys match—allowing secure communication to be established.

**Note:**

- When you run a scenario, if secure communication cannot be established between a secure host (Controller or load generator) and another host participating in the scenario run, the scenario cannot run.
- By definition, non-secure hosts can communicate with each other and participate in scenario runs over non-secure channels.

This can be summarized in the following table:

	<b>Both Hosts in Secure Mode</b>	<b>Security Mode on Hosts Differ</b>	<b>Both Hosts in Non-Secure Mode</b>
<b>Security keys match</b>	Scenario runs over secure channel	Scenario runs over non-secure channel	Scenario runs over non-secure channel
<b>Security keys do not match</b>	Scenario does not run	Scenario does not run	Scenario runs over non-secure channel

## Host Security Configuration

When you install the hosts (Controllers and load generators), by default no security settings are defined on them, and communication channels between the hosts are not secure. To enforce secure communication between the hosts, you must configure security settings on each host machine immediately after installing the hosts.

When configuring these settings **for the first time**, to avoid configuration over non-secure channels, we recommend setting the security on each host locally using the **Host Security Setup** utility. For details, see "[How to Configure Security Settings Locally on Hosts](#)" on page 1335.

After initial security configuration, you can update security settings locally or simultaneously across all the hosts in the LoadRunner system from a remote location using the **HP Host Security Manager** utility. This utility is installed on the same machine as the Controller. For details, see "[How to Update Host Security Settings Remotely](#)" on page 1336.

## Remote Security Configuration

You can align security settings across all the hosts in LoadRunner simultaneously from a remote location using **HP Host Security Manager**.

The utility lists all the hosts in LoadRunner, as well as the MI Listeners required to connect to the hosts that are over a firewall, where applicable.


Using **Host Security Manager**, you can update the security key on all the hosts, or update the security mode on selected hosts. For details, see "[How to Update Host Security Settings Remotely](#)" on page 1336.

### Master Security Key

To update security settings on the hosts, Host Security Manager uses a master key that matches the security keys on all the hosts. This enables secure communication between Host Security Manager and the hosts for the purpose of remotely updating the security settings.

If the master key and security key on a particular host do not match, Host Security Manager cannot update security settings on that host.

When you open Host Security Manager for the first time, you are prompted for a key. Host Security Manager stores this key as a master key for secure communication with the hosts. If you do not enter the key at this point, you are prompted for it again when you try to update the security settings.



## Considerations for Updating Linux Load Generators

- Linux load generators that use rsh (remote shell) to connect to the Controller cannot be updated using Host Security Manager. To update security settings on such load generators, use the local Host Security Setup utility. See "[How to Configure Security Settings Locally on Hosts](#)" on the [next page](#) for Linux load generators on "[How to Configure Security Settings Locally on Hosts](#)" on the [next page](#).
- To update security settings on a Linux load generator using Host Security Manager, you must launch the load generator daemon for a user and manually grant write permissions to the user on <installation folder>/config.

## Host Security Best Practices

- To avoid sending security settings over a non-secure channel, perform **initial configuration** of the security settings on each host locally (see "[How to Configure Security Settings Locally on Hosts](#)" on the [next page](#)).
- Security settings should be changed once a month.

- Security settings can be updated:
  - Manually on each host
  - Remotely on all hosts simultaneously using the Host Security Manager utility

If, when using the Host Security Manager utility, updating a host's settings fails, update the settings manually.

## **How to Configure Security Settings Locally on Hosts**

This task describes how to configure security settings locally on Controllers and load generators.

### **Windows Hosts**

1. On the host, launch the Host Security Setup utility (**Start > All Programs > HP Software > HP LoadRunner > Tools > Host Security Setup**).
- For user interface details, see "[Host Security Setup Dialog Box](#)" on page 1340.
2. Select a security mode for the host.
  3. If you selected to enforce secure communication, enter a security key (6 - 16 characters). Enter the key a second time for confirmation.

### **Linux Hosts**

1. Log in as root user and change to tcsh.
2. Go to the **/opt/HP/HP\_LoadGenerator** folder and type:  

```
>source ./env.csh
```
3. Run **SecurityKeyConsole.exe**, located in **<Installation\_folder>/bin/** folder.



4. In the Console window, enter an option as follows:
  - To change the security mode, enter 1.

- To change the security key, enter 2.
5. If you are changing the security mode:
- To turn the security on, enter 1.
  - To turn the security off, enter 0.
6. If you are changing the security key, enter the new key. A valid key is 6 - 16 characters long.

## **How to Register Hosts in Host Security Manager**

This task describes how to register hosts in Host Security Manager.

### **1. Add hosts to the Hosts list**

In Host Security Manager (**Start > All Programs > HP Software > HP LoadRunner > Tools >** Host Security Manager), click **Add Hosts**.

Enter the names or IP addresses of the Controllers and load generators you want to add. When entering multiple hosts, separate entries by a comma.

For user interface details, see "[Add Hosts Dialog Box](#)" on page 1338.

### **2. For hosts over a firewall, specify the MI Listener**

In the main Host Security Manager window:

- a. Select the host that is over the firewall. If other hosts over a firewall communicate through the same MI Listener, select these hosts as well to set the MI Listener for all of the hosts simultaneously.

**Tip:** To select multiple hosts, hold down the CTRL key on your keyboard while selecting the relevant hosts.

- b. Click **Set MI Listener**, and enter the name / IP address of the MI Listener that the host uses to communicate over the firewall.

## **How to Update Host Security Settings Remotely**

This task describes how to use Host Security Manager to update security settings on the LoadRunner hosts remotely, from the Controller.

### **Prerequisites**

- Hosts to be updated must be registered in Host Security Manager. For details, see "[How to Register Hosts in Host Security Manager](#)" above.

- Hosts in the Host Security Manager list that are not relevant must be deleted from the list.
- Each host must have a security key defined on it, and all of the hosts' security keys must be identical.
- Host Security Manager must have a master security key that is identical to the security key on all of the hosts. For details, see ["Remote Security Configuration" on page 1333](#).

## Update the security settings

1. Open Host Security Manager (**Start > All Programs > HP Software > HP LoadRunner > Tools >** Host Security Manager).
2. Update the desired security setting:
  - **Security key.** Click **Update Security Key**, enter the new key, and enter it again for confirmation.
  - **Security Mode.** Select the hosts in the list that you want to update. To select multiple hosts, hold down the **CTRL** key on your keyboard while selecting the relevant hosts. Click **Update Security Mode**, and select a security mode.
3. Click **Update**.

Host Security Manager attempts to update the security setting on the hosts listed under **Update progress**. As it attempts to update each host, it displays the update status, **Updated** or **Failed**, before attempting to update the next host.

If a host is not updated successfully, check for possible reasons. You can stop the update process by clicking **Stop**.

If there is a mismatch between Host Security Manager's master security key and the host's security key, the Update Error dialog box opens, prompting you for an appropriate action:

- **Skip host.** Skip updating this host.
- **Establish a secure channel using this key.** Use a different security key to communicate securely with the host.
- **Communicate over non-secure channel.** Update the security setting over a non-secure channel. **This action is not recommended**, especially when updating the host security to secure mode. You should rather update the security setting locally on the host (see ["How to Configure Security Settings Locally on Hosts" on page 1335](#)).

To apply the selected action to all similar mismatches, select **Use this solution with all similar mismatches**.

**Note:** The security key update also updates Host Security Manager's master security key. If the update fails on all the hosts, the Host Security Manager's master key is not updated.

## Results

If the update was successful, Host Security Manager displays the time and status of the security key/mode update for each host.

## How to Change a Certificate

LoadRunner allows you to configure the certificates for your test run, in order to secure your testing environment.

To change the CA and SSL certificates used to authenticate between the Controller and load generator:

1. Create or obtain a CA certificate file. For details on how to create a CA certificate file, see ["How to Create and Use Digital Certificates" on page 1346](#). Once you create a CA certificate, you must use it for all of the LoadRunner components.
2. In the Controller, select **Tools > Authentication Settings**. The Authentication Settings dialog box opens. For details, see ["Authentication Settings Dialog Box" on page 1244](#).
3. In the **CA certificate file** box, browse for the CA file that you generated or obtained. You only need to do this once, as the certificate is usually valid for several years.
4. **Option 1: Generate a certificate**. Select **Generate certificate automatically** and provide a Common name for the certificate. Browse for file with the CA private key. Click **Advanced Settings** to further customize your settings.
5. **Option 2: Use an existing certificate** Select **Choose an existing certificate file** and browse for an SSL certificate file (.cer extension) for the Load Generator or MI Listener. In order to be trusted, this certificate needs to be have been issued by the same CA as that on the Load Generator or MI Listener. ("the other side").

**Note:** The Host Security feature will be deprecated in future versions of LoadRunner. It is recommended to secure connections using SSL. See the above procedure for choosing SSL certificates on the Controller machine. For information on using certificates on Monitor over Firewall and agent machines, see the [Network and Security Manager](#).

## Add Hosts Dialog Box

This window enables you to add hosts to the Hosts list in Host Security Manager.

<b>To access</b>	<b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Tools &gt; Host Security Manager &gt; Add Hosts</b>
<b>Relevant tasks</b>	<a href="#">"How to Register Hosts in Host Security Manager" on page 1336</a>

User interface elements are described below:


UI Element	Description
 Add	Adds the Controller and load generators to the list of hosts.
<b>Controller (name or IP)</b>	Enter the name or IP address of the Controller you want to register in Host Security Manager. <b>Note:</b> You can enter more than one Controller at a time, separated by commas.
<b>Load Generators (name or IP), separated by commas</b>	Enter the names or IP addresses of the load generator hosts you want to register in Host Security Manager. <b>Note:</b> You can enter more than one load generator at a time, separated by commas.

## Host Security Manager Window

This window enables you to update security settings remotely on all of the hosts in the load testing system.

To access	<b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Tools &gt; Host Security Manager</b>
Important information	<ul style="list-style-type: none"><li>You must provide Host Security Manager with a master security key before you can update the security settings.</li><li>Every time you use Host Security Manager to update security settings, make sure that the list of hosts is up to date. Hosts that were added to the system must be added to the list, and those deleted, should be deleted from the list.</li></ul> <p>To add a host, see "<a href="#">How to Register Hosts in Host Security Manager</a>" on page <a href="#">1336</a>. To delete a host, select it and click <b>Delete</b>.</p>
Relevant tasks	<a href="#">"How to Update Host Security Settings Remotely"</a> on page 1336
See also	<a href="#">"Secure Host Communication Overview"</a> on page 1331

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
 Add Hosts...	Opens the Add Hosts dialog box where you can register hosts in Host Security Manager.
 Delete	Enables you to delete hosts from the Hosts list in Host Security Manager.

<b>Set MI Listener...</b>	Enables you provide the name/IP address of the MI Listener that the host (or hosts) uses to communicate over the firewall.
<b>Update Security Key...</b>	Opens the Update Security Key dialog box where you can update the security key on all the hosts.
<b>Update Security Mode...</b>	Opens the Update Security Mode dialog box where you can update the security mode on selected hosts.
<b>Set Master Key...</b>	Opens the Set Master Key dialog box where you update Host Security Manager's master security key.
<b>History...</b>	Opens the History dialog box where you can view the history of updates made to the hosts. The information displayed includes the date of the update, the operation (key/mode update), and the update status (Passed/Failed).
<b>&lt;Hosts table&gt;</b>	<p>Displays the following information:</p> <ul style="list-style-type: none"><li>• <b>Host Name/IP.</b> The name or IP address of the host.</li><li>• <b>Host Type.</b> The type of host: Controller / Load Generator.</li><li>• <b>MI Listener.</b> When the host is over a firewall, the name of the MI Listener through which the host communicates with the other hosts.</li><li>• <b>Last Key Update.</b> The last time the security key was updated.</li><li>• <b>Key Update Status.</b> The status of the last security key update.</li><li>• <b>Last Security Mode Update.</b> The last time the security mode was updated.</li><li>• <b>Security Mode Update Status.</b> The status of the last security mode update.</li></ul> <p><b>Tip:</b> You can sort the details on this page in ascending or descending order by clicking the heading of the column by which you want to sort. Click the column heading again to reverse the sort order.</p>

## Host Security Setup Dialog Box

This dialog box enables you to update a host's security settings manually.

<b>To access</b>	On the Controller machine, select <b>Start &gt; All Programs &gt; HP Software &gt; HP LoadRunner &gt; Tools &gt; Host Security Setup</b>
------------------	------------------------------------------------------------------------------------------------------------------------------------------

<b>Important information</b>	When configuring security settings on hosts for the first time, to avoid configuration over non-secure channels, it is recommended to configure security settings on each host locally using the Host Security Setup utility. After initial security configuration, you can update security settings locally, or simultaneously across all the hosts in the LoadRunner system from the Controller using the HP Host Security Manager utility. For details, see " <a href="#">Remote Security Configuration</a> " on page 1333.
<b>Relevant tasks</b>	<a href="#">"How to Configure Security Settings Locally on Hosts" on page 1335 (Windows)</a>
<b>See also</b>	<a href="#">"Host Security Configuration" on page 1333</a>

User interface elements are described below:

UI Element	Description
<b>Select a security mode</b>	Select one of the following security modes: <ul style="list-style-type: none"><li><b>Allow non-secure communication.</b> Allows the host to communicate with other machines over a non-secure channel. (Default)</li><li><b>Enforce secure communication.</b> Enforces the host to communicate with other machines over a secure channel. If you select this option, you must provide the key (6 - 16 characters long) matching the security key on the other hosts with which it needs to communicate.</li></ul>

## ***Update Security Key Dialog Box***

This dialog box enables you to update the security key simultaneously on all the hosts.

<b>To access</b>	Host Security Manager > <b>Update Security Key</b> button
<b>Important information</b>	When you update the security key, the Host Security Manager's master security key is also updated. If the update fails on all the hosts, the Host Security Manager's master key is not updated.
<b>Relevant tasks</b>	<a href="#">"How to Update Host Security Settings Remotely" on page 1336</a>

User interface elements are described below:

UI Element	Description
 <b>Update</b>	Updates the security key on all of the hosts.
 <b>Stop</b>	Stops updating the hosts.

<b>Security Key/Confirm Security Key</b>	Enter the new security key to be updated on all of the hosts, and a second time for confirmation. <b>Note:</b> The key must be 6 - 16 characters long.
<b>Update progress</b>	Displays the hosts and their status during and after the update.

## Update Security Mode Dialog Box

This dialog box enables you to update the security mode simultaneously on selected hosts.

<b>To access</b>	Host Security Manager > <b>Update Security Mode</b> button
<b>Relevant tasks</b>	<a href="#">"How to Update Host Security Settings Remotely" on page 1336</a>

User interface elements are described below:

UI Element	Description
 <b>Update</b>	Updates the security mode on the selected hosts.
 <b>Stop</b>	Stops updating the hosts.
<b>Secure mode</b>	Select a security mode: <ul style="list-style-type: none"><li>• <b>Non-secure.</b> Allows non-secure communication.</li><li>• <b>Secure.</b> Enforces secure communication</li></ul>
<b>Update progress</b>	Displays the hosts, their previous status (if known), and their status during and after the update.

## Troubleshooting and Limitations - Secure Host Communication

This section describes troubleshooting for secure host communication.

### Cannot Run Scenario Over Secure Channels

**Problem description:** When you try to run a scenario over secure channels, the scenario cannot initialize because cannot connect to Controller or load generator.

**Solution:** Verify that the reason the scenario cannot run is because of a security key mismatch by running the same scenario with the same hosts from a local Controller.

If a Security Key Mismatch error is displayed in the error log, then the keys do not match and you need to align the security keys on all the host machines.

## Scenario Run Fails. Load Generator Status is Changed to Resource Failure

**Problem description:** When trying to run a scenario over secure channels, the scenario fails to run and the load generator status changes to **Resource Failure**.

**Solution:** When trying to run a scenario over secure channels, if the security keys on the Controller and load generator do not match the scenario run fails, and the status of the load generators changes to **Resource Failure**. To re-enable the load generators, manually reset the status on each affected load generator to **Operational**.

# Controller Command Line Arguments

## ***Controller Command Line Arguments Overview***

When you invoke the Controller from the command line, you can pass arguments to instruct the Controller how to behave. By passing arguments in the command line, you configure Controller scenario settings without the need to manually define them using the Controller UI.

When invoked, the Controller checks all of the received arguments and sets its start-up environment accordingly. If no arguments are passed, the Controller uses its default settings.

For example, you can instruct Controller to Connect to HP Application Lifecycle Management on start-up, save results to a folder other than the folder defined in the scenario, and invoke Analysis upon scenario termination.

For information on how to invoke the Controller from the command line, see "[Invoke the Controller from the Command Line](#)" below.

For a list of rules relating to invoking the Controller from the command line, see "[Command Line Arguments - Rules](#)" on the next page.

## ***Invoke the Controller from the Command Line***

This task describes how to invoke the Controller from the command line and enter command line arguments.

### **Prerequisite**

Before invoking the Controller from the command line, you should be familiar with the rules relating to command line arguments. For details, see "[Command Line Arguments - Rules](#)" on the next page.

### **Invoke the Controller from the command line and enter the desired command line arguments**

Type wlrun in the command line, followed by the desired arguments.

#### **Notes:**

- The arguments are case sensitive.

- Each argument should be preceded by a dash.

**Example:**

```
wlrun -TestPath C:\LoadRunner\scenario\Scenario.lrs -Run
```

## **Command Line Arguments - Rules**

When you invoke the Controller from the command line, the following rules apply:

- If the Controller is invoked with no arguments in the command line, the Controller uses its default settings.
- The Controller will always overwrite results.
- The Controller will automatically terminate upon scenario termination and results will be collected. If you don't want the Controller to automatically terminate upon scenario termination, add the flag -DontClose to the command line.
- The Controller launched through the command line behaves normally except when using the -Run option. Using the -Run option, dialogs and message boxes that usually open and require the user to close them in a usual launch, do not open in a command line launch.
- The Controller's settings are loaded from **wlrun5.ini**, located in Windows folder.

## **Application Lifecycle Management Arguments**

These arguments define the LoadRunner integration with Application Lifecycle Management. For more information about the LoadRunner Application Lifecycle Management integration, see ["Managing Scenarios Using Application Lifecycle Management" on page 1229](#).

<b>ConnectToQC</b>	Specifies whether the Controller should connect to ALM on startup ( <b>0/1</b> or <b>ON/OFF</b> )
<b>QCServer</b>	Application Lifecycle Management server name. Must be a machine where Application Lifecycle Management is installed
<b>QCDB</b>	Application Lifecycle Management database name. Use the format: <b>&lt;Domain name&gt;.&lt;Project name&gt;</b> .
<b>UserName</b>	User name for connecting to Application Lifecycle Management
<b>Password</b>	Password corresponding to the user name

<b>TestPath</b>	Path to scenario in Application Lifecycle Management database. For example, "[TD]\Subject\LoadRunner\Scenario1" If path includes blank spaces, use quotation marks.
<b>TestId</b>	Test ID (used by ALM only)
<b>ResultCleanName</b>	For use with <b>ResultCycle</b> only. Example: "Res1"
<b>ResultCycle</b>	Application Lifecycle Management cycle. For example, "LR_60_SP1_247" <b>Note:</b> The <b>ResultCycle</b> and <b>ResultCleanName</b> arguments are required if you wish to store the results within the Application Lifecycle Management database.

## Run Time Arguments

These arguments specify the run-time related scenario settings. For more information on scenario settings, see "[Before Running Your Scenario](#)" on page 1185.

<b>TestPath</b>	Path to the scenario, for example, C:\LoadRunner\scenario\Scenario.lrs This argument can also be used for a scenario residing in an Application Lifecycle Management database. For example, "[TD]\Subject\LoadRunner\Scenario1" If the path includes blank spaces, use quotation marks.
<b>Run</b>	Runs the scenario, dumps all output messages into <b>res_dir\output.txt</b> , and closes Controller
<b>InvokeAnalysis</b>	Instructs LoadRunner to invoke Analysis upon scenario termination. If this argument is not specified, LoadRunner uses the scenario default setting.
<b>ResultName</b>	Full results path. For example, "C:\Temp\Res_01"
<b>ResultCleanName</b>	Results name. For example, "Res_01"
<b>ResultLocation</b>	Results folder. For example, "C:\Temp"

## Working with Digital Certificates

### Digital Certificates Overview

A Digital Certificate is an electronic "credit card" that establishes your credentials when doing business or other transactions on the Web. It is issued by a Certification Authority (CA). It contains the IP address of the machine for which it was issued, a validation date, and the digital signature of the certificate-issuing authority.

Certificates created by LoadRunner utilities have following attributes:

- Signature hash algorithm: sha256
- Encryption algorithm: RSA (2048 Bits)

## ***Using Digital Certificates with Firewalls***

When the MI Listener sends its Public Key to the LoadRunner agent, it always sends its certificate as well (this is the server-side certificate). The LoadRunner agent can be configured to authenticate the certificate which it received, as described in "[Working with Firewalls in LoadRunner](#)" on page 1232. If the agent is configured to authenticate the certificate, it can verify whether the sender is really the machine that it claims to be by:

- Comparing the certificate's IP address with the sender's IP address
- Checking the validation date
- Looking for the digital signature in its Certification Authorities list

The MI Listener may also require the LoadRunner agent to send a certificate at any point in the session. This is called the client-side certificate, as described in the MI Listener Configuration Settings in "[Working with Firewalls in LoadRunner](#)" on page 1232. If the LoadRunner agent owns a certificate, it sends it to the MI Listener for the same authentication process. If the LoadRunner agent does not own a certificate, the communication might not be continued.

An SSL CA list and an SSL Certificate are included in each LoadRunner installation. This certificate is the same for all LoadRunner installations, which means that it can be obtained by third parties. Therefore, if you are interested in a more secure process, you should create your own Certificate Authority and include it in the list, and issue matching certificates for your machines.

## ***How to Create and Use Digital Certificates***

This task describes how to create a Certification Authority and a Digital Certificate.

### **1. Create a Certification Authority (CA)**

**Note:** This step describes how to create a CA using the **gen\_ca\_cert.exe** utility. If you are working on a Linux platform, use the **gen\_ca\_cert** utility instead.

To create the CA, perform the following steps:

- a. Run the **gen\_ca\_cert** utility from the <LoadRunner root folder>\bin folder.
- b. Run the **gen\_ca\_cert** command with at least one of the following options:
  - -country\_name

- -organization name
- -common\_name

This process creates two files in the folder from which the utility was run: the CA Certificate (**cacert.cer**), and the CA Private Key (**capvk.cer**). To provide different file names, use the **-CA\_cert\_file\_name** and the **-CA\_pk\_file\_name** options respectively.

**Note:** By default, the CA is valid for three years from when it is generated. To change the validation dates, use the **-nb\_time** (beginning of validity) and/or **-na\_time**(end of validity) options.

The following example creates two files: **ca\_igloo\_cert.cer** and **ca\_igloo\_pk.cer** in the current folder:

```
gen_ca_cert -country_name "North Pole" -organization_name "Igloo Makers"  
-common_name "ICL" -CA_cert_file_name "ca_igloo_cert.cer" -CA_pk_file_name  
"ca_igloo_pk.cer" -nb_time 10/10/2013 -na_time 11/11/2013
```

c. Install the CA using one of the following options:

- **-install <name of certificate file>**. Replaces any previous CA list and creates a new one that includes this CA only.
- **-install\_add <name of certificate file>**. Adds the new CA to the existing CA list.

**Note:** The **-install** and **-install\_add** options install the certificate file only. Keep the private key file in a safe place and use it only for issuing certificates.

## 2. Create a Digital Certificate

**Note:** This step describes how to create a digital certificate using the **gen\_cert.exe** utility. If you are working on a Linux platform, use the **gen\_cert** utility instead.

To create a digital certificate, perform the following steps:

- a. Run the **gen\_cert** utility from the **<LoadRunner root folder>\bin** folder.
- b. Run the **gen\_cert** command with at least one of the following options:
  - **-country\_name**
  - **-organization\_name**
  - **-organization\_unit\_name**
  - **-eMail**

- **-common\_name**

It is important to note the following:

- The CA Certificate and the CA Private Key files are necessary for the creation of the certificate. By default, it is assumed that they are in the current folder, and are named **cacert.cer** and **capvk.cer** respectively. In any other case, use the **-CA\_cert\_file\_name** and **-CA\_pk\_file\_name** options to give the correct files and locations.
- The certificate file is created in the folder from which the utility was run. By default, the file name is **cert.cer**. To provide a different name, use the **-cert\_file\_name** option.

## Troubleshooting and Limitations - Controller

This section contains troubleshooting and limitations for Controller.

### Network Virtualization with Shunra NV

- For scenarios created with Shunra NV 8.6, the Bandwidth Utilization measurement will only be represented on Shunra NV Graphs when Bandwidth Utilization is configured in Shunra NV 8.6 as Shared Bandwidth Utilization. If Bandwidth Utilization is configured as Per User Utilization, Bandwidth Utilization in the Shunra NV graphs will not appear.
- For scenarios created with Shunra Network Virtualization in versions prior to 8.6, LoadRunner automatically represents Bandwidth Utilization measurements as Shared Bandwidth Utilization, and not as Per User Utilization.
- In scenarios with network virtualization, if the Shunra service is restarted during a scenario run, the network virtualization may fail. Check the service and restart the scenario run. For Shunra NV specific limitations and system requirements, refer to Shunra NV documentation.
- Monitoring over a firewall is not supported for scenarios with network virtualization.
- Network virtualization integration does not comply with accepted Internationalization (I18N) conventions.
- The network virtualization software may consume large amounts of memory, since the technology delays traffic and captures traffic for later analysis. To verify that the load generator machine has sufficient memory, compare the load generator memory consumption with and without the virtualization.
- Network virtualization software integration is not supported for the Linux platform.
- You cannot run a scenario on the same load generator from two different Controller machines, if they both have network virtualization enabled.

## Load Generators

- On Load Generator machines with RHEL6 64-bit Linux: If the Controller requires excessive time to transfer the scripts without noticeable progress, this may be a Linux kernel issue. For example, Kernel version 2.6.32-71.el6.x86\_64, may not be able to create new threads.

**Workaround:** Type **uname -a** in the shell to get your kernel version. Log in as root, upgrade the kernel versions for your system and restart using the following commands:

```
yum update kernel  
yum update kernel.x86_64  
shutdown -r now.
```

## Virtual Machines

LoadRunner supports VMware ESX versions 3.0, 3.5, 4.0, 4.1, and 5.0. Running Vusers on virtual machines may adversely affect performance due to the sharing of physical resources.

## Diagnostics for J2EE/.Net Requirements

A unique transaction name must be used for each scenario.

## GUI Vusers

- LoadRunner supports GUI Vuser scripts created using Unified Functional Testing. GUI Vuser scripts created in WinRunner are not supported.
- Windows Load Generator machines can only run one GUI Vuser at a time. To run multiple GUI Vusers in a load test, you need to open a terminal server session for each GUI Vuser. For more information, see the LoadRunner Controller User Guide.

# Analysis

Welcome to the HP LoadRunner Analysis User Guide. This guide describes how to use the LoadRunner Analysis graphs and reports in order to analyze system performance.

You use Analysis after running a load test scenario in the HP LoadRunner Controller or HP Performance Center.

HP LoadRunner, a tool for performance testing, stresses your entire application to isolate and identify potential client, network, and server bottlenecks.

HP Performance Center implements the capabilities of LoadRunner on an enterprise level.


## Working with Analysis

### Introduction to Analysis

#### *Analysis Overview*

Welcome to LoadRunner Analysis, HP's tool for gathering and presenting load test data. When you execute a load test scenario, Vusers generate result data as they perform their transactions. The Analysis tool provides graphs and reports enabling you to view and understand the data.

Each graph has a legend which describes the metrics in the graph. You can also filter your data and sort it by a specific field.



To monitor the scenario performance *during* test execution, use the online monitoring tools described in the Controller section of this guide. To view a summary of the results *after* test execution, use one or more of the following tools:

- **Vuser log files.** These files contain a full trace of the load test scenario run for each Vuser. These files are located in the scenario results folder. (When you run a Vuser script in standalone mode, these files are stored in the Vuser script folder.)
- **Controller Output window.** The output window displays information about the load test scenario run. If your scenario run fails, look for debug information in this window.
- **Analysis Graphs.** Standard and protocol-specific graphs help you determine system performance and provide information about transactions and Vusers. You can compare multiple graphs by combining results from several load test scenarios or merging several graphs into one.
- **Analysis Graph Data and Raw Data Views.** These views display the actual data used to generate the graph in a spreadsheet format. You can copy this data into external spreadsheet applications for further processing.
- **Analysis Reports.** This utility enables you to generate a summary of each graph. The report summarizes and displays the test's significant data in graphical and tabular format. You can generate reports based on customizable report templates.

## Analysis Basics



This section describes basic concepts that will enhance your understanding of how to work with Analysis.

### Creating Analysis Sessions

When you run a load test scenario, LoadRunner stores the run-time data in a result file with an **.Irr** extension. LoadRunner **Analysis** is the utility that processes this data and generates graphs and reports.

When you work with the LoadRunner Analysis, you work within an **Analysis session**. This session contains one or more sets of scenario results (**.Irr** file). Analysis stores the display information and layout settings for the active graphs in a file with an **.Ira** extension.

### Starting Analysis

You can open Analysis as an independent application or directly from the Controller. To open Analysis as an independent application, choose one of the following:

- Start > All Programs > HP Software > HP LoadRunner > Analysis
- The Analysis shortcut on the desktop

To open Analysis directly from the Controller, click the **Analysis** button  on the toolbar or select **Results > Analyze Result**. This option is only available after running a load test scenario.

Analysis takes the latest result file from the current scenario, and opens a new session using these results. You can also instruct the Controller to automatically open Analysis after it completes scenario execution by selecting **Results > Auto Load Analysis**.

## Collating Execution Results

When you run a load test scenario, by default all Vuser information is stored locally on each Vuser host. After scenario execution, the results from all of the hosts are automatically collated or consolidated in the results folder.

You disable automatic collation by choosing **Results > Auto Collate Results** from the Controller window, and clearing the check mark adjacent to the option. To manually collate results, choose **Results > Collate Results**. If your results have not been collated, Analysis will automatically collate the results before generating the analysis data.

## Troubleshooting

If the behavior of Analysis is unpredictable and unexpected messages appear, this might be a result of UAC Virtualization being enabled for Analysis. You can disable UAC Virtualization on the **Analysis.exe** process in the Windows Task Manager.

## Analysis Graphs



Analysis graphs are divided into the following categories:

- **Application Component Graphs.** Provide information about resource usage of the Microsoft COM+ server and the Microsoft .NET CLR server. For more information, see "[Application Component Graphs](#)" on page 1595.
- **Application Deployment Solutions Graphs.** Provide information about resource usage of the Citrix MetaFrame server. For more information, see "[Application Deployment Solutions Graphs](#)" on page 1619.
- **Database Server Resource Graphs.** Provide information about database resources. For more information, see "[Database Server Resource Graphs](#)" on page 1554.
- **ERP/CRM Server Resource Graphs.** Provide information about ERP/CRM server resource usage. For more information, see "[ERP/CRM Server Resource Graphs](#)" on page 1581.
- **Error Graphs.** Provide information about the errors that occurred during the load test scenario. For more information, see "[Error Graphs](#)" on page 1478.
- **Firewall Server Monitor Graphs.** Provide information about firewall server resource usage. For

more information, see "[Firewall Server Graphs](#)" on page 1540.

- **Flex RTMP Graphs.** Provide information about resource usage of the Flex server. For more information, see "[Flex Graphs](#)" on page 1469.
- **Infrastructure Resources Graphs.** Provide information about resource usage of FTP, POP3, SMTP, IMAP, and DNS Vusers on the network client. For more information, "[Infrastructure Resources Graphs](#)" on page 1631.
- **J2EE & .NET Diagnostics Graphs.** Provide information to trace, time, and troubleshoot individual transactions through J2EE & .NET Web, application, and database servers. For more information, see "[J2EE & .NET Diagnostics Graphs](#)" on page 1708.
- **Middleware Performance Graphs.** Provide information about resource usage of the Tuxedo and IBM WebSphere MQ servers. For more information, see "[Middleware Performance Graphs](#)" on page 1625.
- **Network Monitor Graphs.** Provide information about the network delays. For more information, see "[Network Monitor Graphs](#)" on page 1498.
- **Oracle 11i Diagnostics Graphs.** Provide detailed breakdown diagnostics for SQLs generated by transactions on the Oracle NCA system. For more information, see "[Oracle 11i Diagnostics Graphs](#)" on page 1684.
- **SAP Diagnostics Graphs.** Provide detailed breakdown diagnostics for SAP data generated by transactions on the SAP Server. For more information, see "[SAP Diagnostics Graphs](#)" on page 1691.
- **Siebel Diagnostics Graphs.** Provide detailed breakdown diagnostics for transactions generated on Siebel Web, Siebel App, and Siebel Database servers. For more information, see "[Siebel Diagnostics Graphs](#)" on page 1661.
- **Siebel DB Diagnostics Graphs.** Provide detailed breakdown diagnostics for SQLs generated by transactions on the Siebel system. For more information, see "[Siebel DB Diagnostics Graphs](#)" on page 1675.
- **Streaming Media Graphs.** Provide information about resource usage of streaming media. For more information, see "[Streaming Media Graphs](#)" on page 1575.
- **System Resource Graphs.** Provide statistics relating to the system resources that were monitored during the load test scenario using the online monitor. This category also includes graphs for SNMP monitoring. For more information, see "[System Resource Graphs](#)" on page 1522.
- **Transaction Graphs.** Provide information about transaction performance and response time. For more information, see "[Transaction Graphs](#)" on page 1459.
- **User-Defined Data Point Graphs.** Provide information about the custom data points that were gathered by the online monitor. For more information, see "[User-Defined Data Point Graphs](#)" on

[page 1495.](#)

- **Vuser Graphs.** Provide information about Vuser states and other Vuser statistics. For more information, see "["Vuser Graphs" on page 1475.](#)
- **Web Application Server Resource Graphs.** Provide information about the resource usage for various Web application servers. For more information see "["Web Application Server Resource Graphs" on page 1545.](#)
- **Web Page Diagnostics Graphs.** Provide information about the size and download time of each Web page component. For more information, see "["Web Page Diagnostics Graphs" on page 1502.](#)
- **Web Resource Graphs.** Provide information about the throughput, hits per second, HTTP responses per second, number of retries per second, and downloaded pages per second for Web Vusers. For more information, see "["Web Resources Graphs" on page 1483.](#)
- **Web Server Resource Graphs.** Provide information about the resource usage for the Apache and MS IIS Web servers. For more information see "["Web Resources Graphs" on page 1483.](#)

## **Analysis API**

The LoadRunner Analysis API enables you to write programs to perform some of the functions of the Analysis user interface, and to extract data for use in external applications. Among other capabilities, the API allows you to create an analysis session from test results, analyze raw results of an Analysis session, and extract key session measurements for external use. An application can be launched from the LoadRunner Controller at the completion of a test. For more information, see the *Analysis API Reference*.

## **Network Virtualization**

LoadRunner integrates with Shunra Network Virtualization for HP Software. This enables you to test point-to-point performance of WAN or other network deployed products under real-world network conditions. By installing software on your load generators, you introduce highly probable effects such as latency, packet loss, and link faults over your network. As a result of this, your scenario performs the test in an environment that better represents the actual deployment of your application.

You can create more meaningful results by configuring multiple load generator machines or groups on a single load generator with the same unique set of network effects, and by giving each set a unique location name, such as NY- London. When viewing scenario results in Analysis, you can group the metrics according to their location names.

For details, see "["Network Virtualization Graphs" on page 1532.](#)

## **How to Customize the Layout of Analysis Windows**

This task describes ways to customize the layout of the windows of the Analysis session.

## Open Windows

You can open a window or restore a window that was closed by selecting the name of the relevant window from the **Windows** menu.

## Lock/Unlock the Layout of the Screen

Select **Windows > Layout Locked** to lock or unlock the layout of the screen.

## Restore the Window Placement to the Default Layout

Select **Windows > Restore Default Layout** to restore the placement of the Analysis windows to their default layout.

**Note:** This option is available only when no Analysis session is open.

## Restore the Window Placement to the Classic Layout

Select **Windows > Restore Classic Layout** to restore the placement of the Analysis windows to their classic layout. The classic layout resembles the layout of earlier versions of Analysis.

**Note:** This option is available only when no Analysis session is open.

## Reposition and Dock Windows

You can reposition any window by dragging it to the desired position on the screen. You can dock a window by dragging the window and using the arrows of the guide diamond to dock the window in the desired position.

**Note:**

- Only document windows (graphs or reports) can be docked in the center portion of the screen.
- **Windows > Layout Locked** must not be selected when repositioning or docking windows.

## Using Auto Hide

You can use the Auto Hide feature to minimize open windows that are not in use. The window is minimized along the edges of the screen.

Click the **Auto Hide** button on the title bar of the window to enable or disable Auto Hide.

## ***Analysis Toolbars***

This section describes the buttons that you access from the main Analysis toolbars.

### Common Toolbar

This toolbar is always accessible from the toolbar at top of the page and includes the following buttons:

User interface elements are described below:

UI Element	Description
	Create a new session.
	Open an existing session.
	Generate a Cross Result graph.
	Save a session.
	Print item.
	Create an HTML report.
	View runtime settings.
	Set global filter options.
	Configure SLA rules
	Analyze a transaction.
	Undo the most recent action.
	Reapply the last action that was undone.
	Apply filter on summary page
	Export Summary to Excel

## Graph Toolbar

This toolbar is accessible from the top of the page when you have a graph open and includes the following buttons


User interface elements are described below:

UI Element	Description
	Set filter settings.
	Clear filter settings.

UI Element	Description
	Set granularity settings.
	Merge graphs.
	Configure auto correlation settings.
	View raw data.
	Add comments to a graph.
	Add arrows to a graph.
	Set display options.

## Session Explorer Window

This window displays a tree view of the items (graphs and reports) that are open in the current session. When you click an item in the Session Explorer, it is activated in the main Analysis window.




<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• <b>Session Explorer</b></li><li>• <b>Session Explorer &gt; Reports &gt; Summary Report</b></li><li>• <b>Session Explorer &gt; Reports &gt; Service Level Agreement Report</b></li><li>• <b>Session Explorer &gt;  &gt; Analyze Transaction</b></li><li>• <b>Session Explorer &gt; Graphs</b></li></ul>
------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

User interface elements are described below:

UI Element	Description
	Add a new graph or report to the current Analysis session. Opens the Open a New Graph dialog box. For details, see " <a href="#">"Open a New Graph Dialog Box" on the next page</a>
	Delete the selected graph or report.
	Rename the selected graph or report.
	Create a copy of the selected graph.

## Open a New Graph Dialog Box

This dialog box enables you to select the graph type to activate in the main Analysis window.



To access

Session Explorer > Graphs >

User interface elements are described below:


UI Element	Description
Select a graph	Displays list of graph types.
Display only graphs containing data	If checked, only graphs that contain data are listed (in blue) in the Select a graph area.
Graph Description	Displays detailed information about the selected graph.

, continued

UI Element	Description
 Open Graph	Analysis generates the selected graph and adds it to the Session Explorer.
 Filter & Open	Opens the graphs Graph Settings dialog box. For details, see " <a href="#">"Filter Dialog Boxes" on page 1405</a> . This option enables you to apply filter conditions on the selected graph before the graph is displayed.

## Print Graphs or Reports

This dialog box enables you to print graphs or reports



<b>To access</b>	Do one of the following:
	<ul style="list-style-type: none"><li>• <b>File &gt; Print</b></li><li>• <b>Main toolbar &gt;</b> </li></ul>

User interface elements are described below:

UI Element	Description
Select Items to Print	<ul style="list-style-type: none"><li><b>All Items.</b> Prints all graphs and reports in the current session.</li><li><b>Current Item.</b> Prints the graph or report currently selected in the Session Explorer.</li><li><b>Specific Item(s).</b> Select the graphs or reports to print.</li></ul>
Include	<ul style="list-style-type: none"><li><b>User Notes.</b> Prints the notes in the User Notes window.</li><li><b>Graph Details.</b> Prints details such as graph filters and granularity settings.</li></ul>

## Configuring Analysis

### ***Summary Data Versus Complete Data***

In large load test scenarios, with results exceeding 100 MB, it can take a long time for Analysis to process the data. When you configure how Analysis generates result data from load test scenarios, you can choose to generate complete data or summary data.

**Complete data** refers to the result data after it has been processed for use within Analysis.

**Summary data** refers to the raw, unprocessed data. The summary graphs contain general information such as transaction names and times. Some fields are not available for filtering when you work with summary graphs.


Note that some graphs will not be available when viewing only the summary data.

### ***Importing Data Directly from the Analysis Machine***

If you are using an SQL server / MSDE machine to store Analysis result data, you can configure Analysis to import data directly from the Analysis machine.


#### **Importing Data from the SQL Server**

If you do not select the option to import data directly from the Analysis machine, Analysis creates CSV files in a local temp folder. The CSV files are copied to a shared folder on the SQL Server machine. The SQL server engine then imports the CSV files into the database. The following diagram illustrates the data flow:



## Importing Data from the Analysis Machine

If you selected the option to import data directly from the Analysis machine, Analysis creates the CSV files in a shared folder on the Analysis machine and the SQL server imports these CSV files from the Analysis machine directly into the database. The following diagram illustrates the data flow:



## ***How to Configure Settings for Analyzing Load Test Results***

The following steps describe how to configure certain Analysis settings that significantly impact the way in which Analysis analyzes load test results.

### **Configure how Analysis processes result data**

You define how Analysis processes result data from load test scenarios in the **Tools > Options > Result Collection** tab. For example, you can configure how Analysis aggregates result data, to what extent the data is processed, and whether output messages are copied from the Controller. For details on the user interface, see "[Result Collection Tab \(Options Dialog Box\)](#)" on page 1366.

### **Configure template settings**


For details on the user interface, see "[Apply/Edit Template Dialog Box](#)" on page 1389.

### **Configure analysis of transactions**

You configure how transactions are analyzed and displayed in the summary report in the **Summary Report** area of the **Tools > Options > General** tab. For details, see the description of "[General Tab \(Options Dialog Box\)](#)" below.

## ***General Tab (Options Dialog Box)***

This tab enables you to configure general Analysis options, such as date formats, temporary storage location, and transaction report settings.



<b>To access</b>	Tools > Options > General tab.
<b>See Also</b>	"How to Configure Settings for Analyzing Load Test Results" on the previous page


User interface elements are described below:

UI Element	Description
<b>Date Format</b>	<p>Select a date format for storage and display. (For example, the date displayed in the Summary report)</p> <ul style="list-style-type: none"> <li>• <b>European.</b> Displays the European date format.</li> <li>• <b>US.</b> Displays the U.S. date format.</li> <li>• <b>Traditional Chinese.</b> Displays the Traditional Chinese date format.</li> <li>• <b>Local Regional Options.</b> Displays the date format as defined in the current user's regional settings.</li> </ul> <p><b>Note:</b> When you change the date format, it only affects newly created Analysis sessions. The date format of existing sessions is not affected.</p>
<b>File Browser</b>	<p>Select the directory location at which you want the file browser to open.</p> <ul style="list-style-type: none"> <li>• <b>Open at most recently used directory.</b> Opens the file browser at the previously used directory location.</li> <li>• <b>Open at specified directory.</b> Opens the file browser at a specified directory.</li> </ul> <p>In the <b>Directory path</b> box, enter the directory location where you want the file browser to open.</p>
<b>Temporary Storage Location</b>	<p>Select the directory location in which you want to save temporary files.</p> <ul style="list-style-type: none"> <li>• <b>Use Windows temporary directory.</b> Saves temporary files in your Windows temp directory.</li> <li>• <b>Use a specified directory.</b> Saves temporary files in a specified directory.</li> </ul> <p>In the <b>Directory path</b> box, enter the directory location in which you want to save temporary files.</p>
<b>Summary Report</b>	<p>Set the following transaction settings in the Summary Report:</p> <ul style="list-style-type: none"> <li>• <b>Transaction Percentile.</b> The Summary Report contains a percentile column showing the response time of 90% of transactions (90% of transactions that fall within this amount of time). To change the value of the default 90 percentile, enter a new figure in the <b>Transaction Percentile</b> box.</li> </ul> <p>The Transaction Percentile value is only applied to newly created templates . To create a new template, select <b>Tools &gt;Templates</b>. For details, see "<a href="#">"Apply/Edit Template Dialog Box" on page 1389</a>".</p>

UI Element	Description
Start Page	Select <b>Show start page on start up</b> to display the <b>Welcome to Analysis</b> tab every time you open the Analysis application.
Graph	Select the way in which graphs shows the Elapsed Scenario Time on the x-axis. <b>Use Absolute time.</b> Shows an elapsed time based on the absolute time of the machine's system clock. If not checked, shows the elapsed time relative to the start of the scenario. The default is unchecked.

## Result Collection Tab (Options Dialog Box)

This tab enables you to configure how Analysis processes result data from load test scenarios.



To access    Tools > Options > Result Collection tab.

<b>Important information</b>	The options in this tab are pre-defined with default settings. It is recommended to use these default settings unless there is a specific need to change them. Changing some of the settings, such as default aggregation, can significantly impact the amount of data stored in the Analysis database.
<b>See Also</b>	<a href="#">"How to Configure Settings for Analyzing Load Test Results" on page 1363</a>

User interface elements are described below:


UI Element	Description
<b>Data Source</b>	<p>In this area, you configure how Analysis generates result data from load test scenarios.</p> <p><b>Complete data</b> refers to the result data after it has been processed for use within Analysis. <b>Summary data</b> refers to the raw, unprocessed data. The summary graphs contain general information such as transaction names and times. For more details on summary data versus complete data, see "<a href="#">"Summary Data Versus Complete Data" on page 1361</a>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"><li>• <b>Generate summary data only.</b> If this option is selected, Analysis will not process the data for advanced use with filtering and grouping.</li><li>• <b>Generate complete data only.</b> If this option is selected, the graphs can then be sorted, filtered, and manipulated.</li><li>• <b>Display summary data while generating complete data.</b> Enables you to view summary data while you wait for the complete data to be processed.</li></ul> <p><b>Note:</b> If you selected one of the options to generate complete data, you can define how Analysis aggregates the complete data in the <b>Data Aggregation</b> area.</p>

UI Element	Description
<b>Data Aggregation</b>	<p>If you chose to generate complete data in the <b>Data Source</b> area, you use this area to configure how Analysis aggregates the data.</p> <p>Data aggregation is necessary in order to reduce the size of the database and decrease processing time in large scenarios.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>• <b>Automatically aggregate data to optimize performance.</b> Aggregates data using built-in data aggregation formulas.</li> <li>• <b>Automatically aggregate Web data only.</b> Aggregates Web data only using built-in data aggregation formulas.</li> <li>• <b>Apply user-defined aggregation.</b> Aggregates data using settings you define.</li> </ul> <p>Click the <b>Aggregation Configuration</b> button to open the Data Aggregation Configuration Dialog Box and define your custom aggregation settings. For details on the user interface, see "<a href="#">"Data Aggregation Configuration Dialog Box (Result Collection Tab)" on the next page.</a></p>
<b>Data Time Range</b>	<p>In this area you specify whether to display data for the complete duration of the scenario, or for a specified time range only. Select one of the following options:</p> <ul style="list-style-type: none"> <li>• <b>Entire scenario.</b> Displays data for the complete duration of the load test scenario</li> <li>• <b>Specified scenario time range.</b> Specify the time range using the following boxes: <ul style="list-style-type: none"> <li>▪ <b>Analyze results from.</b> Enter the amount of scenario time you want to elapse (in hh:mm:ss format) before Analysis begins displaying data.</li> <li>▪ <b>until.</b> Enter the point in the scenario (in hh:mm:ss format) at which you want Analysis to stop displaying data.</li> </ul> </li> </ul> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>• It is not recommended to use the <b>Specified scenario time range</b> option when analyzing the Oracle 11i and Siebel DB Diagnostics graphs, since the data may be incomplete.</li> <li>• The <b>Specified scenario time range</b> settings are not applied to the Connections and Running Vusers graphs.</li> </ul>

UI Element	Description
<b>Copy Controller Output Messages to Analysis Session</b>	<p>Controller output messages are displayed in Analysis in the Controller Output Messages window. Select one of the following options for copying output messages generated by the Controller to the Analysis session.</p> <ul style="list-style-type: none"> <li><b>Copy if data set is smaller than X MB.</b> Copies the Controller output data to the Analysis session if the data set is smaller than the amount you specify.</li> <li><b>Always Copy.</b> Always copies the Controller output data to the Analysis session.</li> <li><b>Never Copy.</b> Never copies the Controller output data to the Analysis session.</li> </ul>
<b>Apply now on active session</b>	Click this button to apply the settings in the Result Collection tab to the current session. The Controller output data is copied when the Analysis session is saved.

## Data Aggregation Configuration Dialog Box (Result Collection Tab)

If you choose to generate the complete data from the load test scenario results, Analysis aggregates the data using either built-in data aggregation formulas, or aggregation settings that you define. This dialog box enables you to define custom aggregation settings.




To access	Select <b>Tools &gt; Options &gt; Result Collection</b> . Select the <b>Apply user-defined aggregation</b> option and click the <b>Aggregation Configuration</b> button.
Important information	In this dialog box, you can select granularity settings. To reduce the size of the database, increase the granularity. To focus on more detailed results, decrease the granularity.

User interface elements are described below:

UI Element	Description
<b>Aggregate Data</b>	<p>Select this option to define your custom aggregation settings using the following criteria:</p> <ul style="list-style-type: none"><li>• <b>Select the type of data to aggregate.</b> Use the check boxes to select the types of graphs for which you want to aggregate data.</li><li>• <b>Select graph properties to aggregate.</b> Use the check boxes to select the graph properties you want to aggregate.</li></ul> <p>To exclude data from failed Vusers, select <b>Do not aggregate failed Vusers</b>.</p> <p><b>Note:</b> You will not be able to drill down on the graph properties you select in this list.</p> <ul style="list-style-type: none"><li>• <b>Select the granularity you want to use.</b> Specify a custom granularity for the data. The minimum granularity is 1 second.</li></ul>
<b>Web data aggregation only</b>	Select this option to aggregate Web data only. In the <b>Use Granularity of X for Web data</b> box, specify a custom granularity for Web data.

## ***Database Tab (Options Dialog Box)***

This tab enables you to specify the database in which to store Analysis session result data and to configure the way in which CSV files will be imported into the database.



**To access**    **Analysis > Tools > Options > Database tab.**

<b>Important information</b>	<p>Analysis data can be saved in one of three formats. Select the format based on the size of the analysis session file, as shown in the table below:</p> <table border="1"><thead><tr><th><b>Size of the Analysis session file</b></th><th><b>Recommended format</b></th></tr></thead><tbody><tr><td>• Less than 2 GB</td><td>Access 2000</td></tr><tr><td>• 2 GB to 10 GB</td><td>SQL Server/MSDE</td></tr><tr><td></td><td><p><b>Note:</b> Select SQL Server/MSDE if you need to work in multithread mode.</p></td></tr><tr><td>• More than 10 GB</td><td>SQLite</td></tr><tr><td></td><td><p><b>Note:</b> The SQLite format allows you to store up to 32 terabytes of data.</p></td></tr></tbody></table> <p><b>Note:</b> Both the Access 2000 database format and the SQLite format are embedded databases. The session directory contains both the database and the analysis data.</p>	<b>Size of the Analysis session file</b>	<b>Recommended format</b>	• Less than 2 GB	Access 2000	• 2 GB to 10 GB	SQL Server/MSDE		<p><b>Note:</b> Select SQL Server/MSDE if you need to work in multithread mode.</p>	• More than 10 GB	SQLite		<p><b>Note:</b> The SQLite format allows you to store up to 32 terabytes of data.</p>
<b>Size of the Analysis session file</b>	<b>Recommended format</b>												
• Less than 2 GB	Access 2000												
• 2 GB to 10 GB	SQL Server/MSDE												
	<p><b>Note:</b> Select SQL Server/MSDE if you need to work in multithread mode.</p>												
• More than 10 GB	SQLite												
	<p><b>Note:</b> The SQLite format allows you to store up to 32 terabytes of data.</p>												
<b>See also</b>	<a href="#">"Importing Data Directly from the Analysis Machine" on page 1361</a>												

User interface elements are described below:

<b>UI Element</b>	<b>Description</b>
<b>Access 2000</b>	Instructs LoadRunner to save Analysis result data in an Access 2000 database format. This setting is the default.
<b>SQL Server/MSDE</b>	Instructs LoadRunner to save Analysis result data on an SQL server / MSDE machine. If you select this option, you have to complete the <b>Server Details</b> and <b>Shared Folder Details</b> , described below.
<b>SQLite</b>	Instructs LoadRunner to save Analysis result data in an SQLite database format.  If you choose this format, you will not be able to work in multithread mode.
<b>Server Details area</b>	SQL server / MSDE machine details. See description below.
<b>Shared Folder Details area</b>	SQL server / MSDE machine shared folder details. See description below.

UI Element	Description
<b>Test parameters</b>	<p>Depending on which database you are using, this button performs the following action:</p> <ul style="list-style-type: none"> <li>• <b>For Access.</b> Checks the connection parameters to the Access database and verifies that the <b>delimiter</b> on your machine's regional settings matches the Microsoft JET delimiter on the database machine.</li> <li>• <b>For SQL server / MSDE.</b> Checks the connection parameters, the existence of a shared server directory, whether there are write permissions on the shared server directory, and whether the shared and physical server directories are synchronized.</li> <li>• <b>For SQLite.</b> This button is disabled.</li> </ul>
<b>Compact database</b>	<p>When you configure and set up your Analysis session, the database containing the results may become fragmented. As a result, it will use excessive disk space. For Access databases, the <b>Compact database</b> button enables you to repair and compress your results and optimize your database. This button is disabled if you choose <b>SQLite</b>.</p> <p><b>Note:</b> Long load test scenarios (duration of two hours or more) will require more time for compacting.</p>
<b>Advanced</b>	<p>Opens the Advanced Options dialog box, allowing you to increase performance when processing LoadRunner results or importing data from other sources. This button is disabled if you choose <b>SQLite</b>. For user interface details see "<a href="#">Advanced Options Dialog Box (Database Tab)</a>" on <a href="#">page 1375</a>.</p>

## Server Details Area

If you choose to store Analysis result data on an SQL server / MSDE machine, you need to complete the server details. User interface elements are described below:

UI Element	Description
<b>Server Name</b>	The name of the machine on which the SQL server / MSDE is running.
<b>Use Windows integrated security</b>	Enables you to use your Windows login, instead of specifying a user name and password. By default, the user name "sa" and no password are used for the SQL server.
<b>User Name</b>	The user name for the master database.
<b>Password</b>	The password for the master database.


## Shared Folder Details Area

If you store Analysis result data on an SQL server / MSDE machine, you need to provide the shared folder details. User interface elements are described below:

UI Element	Description
<b>Import Data Directly from Analysis machine</b>	<p>Select this option to import data directly from the Analysis machine. For details on this option, see "<a href="#">Importing Data Directly from the Analysis Machine</a>" on page <a href="#">1361</a>.</p>
<b>Shared Folder on MS SQL Server</b>	<ul style="list-style-type: none"> <li>• <b>Shared folder path.</b> Enter a shared folder on the SQL server / MSDE machine. For example, if your SQL server's name is f1y, enter \\f1y\&lt;Analysis database folder&gt;\.</li> </ul> <p>This folder has different functions, depending on how you import the Analysis data:</p> <ul style="list-style-type: none"> <li>▪ <b>If you did not select the option to import data directly from the Analysis machine,</b> this folder stores permanent and temporary database files. Analysis results stored on an SQL server / MSDE machine can only be viewed on the machine's local LAN.</li> <li>▪ <b>If you selected the option to import data directly from the Analysis machine,</b> this folder is used to store an empty database template copied from the Analysis machine.</li> <li>• <b>Local folder path.</b> Enter the real drive and folder path on the SQL server / MSDE machine that correspond to the above shared folder path. For example, if the Analysis database is mapped to an SQL server named f1y, and f1y is mapped to drive D, enter D:\&lt;Analysis database folder&gt;.</li> </ul> <p>If the SQL server / MSDE and Analysis are on the same machine, the logical storage location and physical storage location are identical.</p>
<b>Shared Folder on Analysis Host</b>	<p>If you selected the option to import data directly from the Analysis machine, the <b>Shared folder path</b> box is enabled. Analysis detects all shared folders on your Analysis machine and displays them in a drop-down list. Select a shared folder from the list.</p> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>• Ensure that the user running the SQL server (by default, SYSTEM) has access rights to this shared folder.</li> <li>• If you add a new shared folder on your machine, you can click the refresh  button to display the updated list of shared folders.</li> <li>• Analysis creates the CSV files in this folder and the SQL server imports these CSV files from the Analysis machine directly into the database. This folder stores permanent and temporary database files.</li> </ul>

## Advanced Options Dialog Box (Database Tab)

This dialog box enables you to increase performance when processing LoadRunner results or importing data from other sources.




To access	Tools > Options > Database tab > Advanced button
See also	<a href="#">"Database Tab (Options Dialog Box)" on page 1370</a>

User interface elements are described below:

UI Element	Description
<b>Create separate threads for inserting Analysis data into the database.</b>	This option may consume a large amount of memory on your database server, and should only be used if you have sufficient memory resources.
<b>Use SQL parameters to utilize the SQL Server memory buffer.</b>	This option is only enabled when you store Analysis result data on an SQL server or MSDE machine.

## Web Page Diagnostics Tab (Options Dialog Box)

This tab enables you to set Web page breakdown options. You can choose how to aggregate the display of URLs that include dynamic information, such as a session ID. You can display these URLs individually, or you can unify them and display them as one line with merged data points.




To access	Tools > Options > Web Page Diagnostics tab
-----------	--------------------------------------------

User interface elements are described below:

UI Element	Description
<b>Display individual URLs</b>	Displays each URL individually
<b>Display an average of merged URLs</b>	Merges URLs from the same script step into one URL, and displays it with merged (average) data points.

## ***Session Information Dialog Box (Options Dialog Box)***

This dialog box enables you to view a summary of the configuration properties of the current Analysis session.



To access	File > Session Information
-----------	----------------------------

User interface elements are described below:

UI Element	Description
<b>Aggregation Properties...</b>	Displays the type of data aggregated, the criteria according to which it is aggregated, and the time granularity of the aggregated data.
<b>Server Properties...</b>	Displays the properties of the SQL server and MSDE databases.
<b>Aggregation</b>	Indicates whether the session data has been aggregated.
<b>Data Collection Mode</b>	Indicates whether the session displays complete data or summary data.
<b>Data Time Filter</b>	Indicates whether a time filter has been applied to the session.
<b>Database Name</b>	Displays the name and directory path of the database.
<b>Database Type</b>	Displays the type of database used to store the load test scenario data.
<b>Results</b>	Displays the name of the LoadRunner result file.

UI Element	Description
<b>Session Name</b>	Displays the name of the current session.
<b>Web Granularity</b>	Displays the Web granularity used in the session.

## Configuring Graph Display

Analysis allows you to customize the display of the graphs and measurements in your session so that you can view the data displayed in the most effective way possible.

### ***How to Customize the Analysis Display***

The following steps describes how to customize the display of analysis. You can customize the display of the graphs and measurements in your session so that you can view the data displayed in the most effective way possible.

#### **Enlarging a section of the graph**

To zoom in or enlarge a section of the graph, move and hold down the left mouse button over the section of the graph you want to enlarge.

#### **Using comments in a graph**

To add a comment to a graph, click  and then click the mouse over the section of the graph where you would like to add a comment. Type your comment in the Add Comment dialog box.

To edit, format or delete a comment from the graph, click the comment and apply your change in the Edit Comments dialog box. In the left pane, verify the relevant comment is selected before you edit, format or delete.

#### **Using arrows in a graph**

To add an arrow to a graph, click  and then click the mouse button within the graph to position the base of the arrow.

To delete an arrow from a graph, select the arrow and press Delete.

#### **Using the User Notes Window**


In the User Notes window (**Windows > User Notes**), you can enter text about the graph or report that is currently open. The text in the User Notes window is saved with the session.

To view the text that you entered for a specific graph or report, select the relevant graph or report and open the User Notes window (**Windows > User Notes**).

## ***Display Options Dialog Box***

This dialog box enables you to select the graph type and configure the display of the graph.

**Note:** This option is not available for all graph types.



To access	View > Display Options
See also	<ul style="list-style-type: none"><li>• <a href="#">"Editing Main Chart Dialog Box (Display Options Dialog Box)" on the next page</a></li><li>• <a href="#">"Chart Tab (Editing MainChart Dialog Box)" on page 1381</a></li><li>• <a href="#">"Series Tab (Editing MainChart Dialog Box)" on page 1382</a></li></ul>


User interface elements are described below:

UI Elements>	Description
Type	Select the type of graph to display from the drop-down list.
Values Types	Select the type of display information from the list of available values. For example, a bar graph displaying Average Transaction Response Time can be configured to display minimum, maximum, average, STD, count, and sum averages.
Graph X Axis (Bar graphs only)	Select the bar arrangement along the x-axis. You can arrange the bars by value types or measurement.
Time Options	Select the way in which the graph shows the Elapsed Scenario Time on the x-axis. You can choose an elapsed time relative to the beginning of the scenario or an elapsed time from the absolute time of the machine's system clock.

UI Elements>	Description
<b>Show Breaking Measurement</b>	Select this check box to display the name and properties of the breaking measurement at the top of the graph (disabled by default).
<b>3 Dimensional</b>	Select this check box to enable a 3-dimensional display of the graph.
<b>3D %</b>	Specify a percentage for the 3-dimensional aspect of lines in the graph. This percentage indicates the thickness if the bar, grid, or pie chart.
<b>Show Legend on Graph</b>	Select this check box to display a legend at the bottom of the graph.
<b>Drawing Arrows</b>	Allows you to configure the style, color, and width of arrows you draw to highlight graph information.
<b>Advanced...</b>	Opens the <b>Editing MainChart</b> dialog box. For more information, see " <a href="#">Editing Main Chart Dialog Box (Display Options Dialog Box)</a> " below.

## ***Editing Main Chart Dialog Box (Display Options Dialog Box)***

This dialog box enables you to configure the look and feel of your graph as well as its title and the format of the data.



To access    View > Display Options > Advanced button

**See also**

- "Display Options Dialog Box" on page 1378
- "Chart Tab (Editing MainChart Dialog Box)" below
- "Series Tab (Editing MainChart Dialog Box)" on the next page

User interface elements are described below:

UI Element	Description
Chart tab	Enables you to configure the look and feel of your entire graph. You set Chart preferences using the following tabs: For details, see "Chart Tab (Editing MainChart Dialog Box)" below.
Series tab	Enables you to control the appearance of the individual points plotted in the graph. You set Series preferences using the following tabs. For details, see "Series Tab (Editing MainChart Dialog Box)" on the next page.
Export tab	Enables you to store the current graph to an image file in the format of your choice—BMP, JPG, or EMF. You can also export the graph's data to HTML, Excel, or XML
Print tab	Enables you to print only the graph itself without the legend and other data such as the User Notes.

## **Chart Tab (Editing MainChart Dialog Box)**

This tab enables you to configure the look and feel of your entire graph.

To access	View > Display Options > Advanced button > Chart tab
See also	<ul style="list-style-type: none"><li>• "Display Options Dialog Box" on page 1378</li><li>• "Editing Main Chart Dialog Box (Display Options Dialog Box)" on the previous page</li><li>• "Series Tab (Editing MainChart Dialog Box)" on the next page</li></ul>


User interface elements are described below:

UI Element	Description
Series tab	Select the graph style (for example, bar or line), the hide/show settings, line and fill color, and the title of the series.

UI Element	Description
<b>General tab</b>	Select options for print preview, export, margins, scrolling, and magnification.
<b>Axis tab</b>	Select which axes to show, as well as their scales, titles, ticks, and position.
<b>Titles tab</b>	Set the title of the graph, its font, background color, border, and alignment.
<b>Legend tab</b>	Set all legend related settings, such as position, fonts, and divider lines.
<b>Panel tab</b>	Show the background panel layout of the graph. You can modify its color, set a gradient option, or specify a background image.
<b>Paging tab</b>	Set all page related settings, such as amount of data per page, scale, and page numbering. These settings are relevant when the graph data exceeds a single page.
<b>Walls tab</b>	Set colors for the walls of 3-dimensional graphs.
<b>3D</b>	Select the 3-dimensional settings, offset, magnification, and rotation angle for the active graph.

## ***Series Tab (Editing MainChart Dialog Box)***

This page enables you to control the appearance of the individual points plotted in the graph.




<b>To access</b>	<b>View &gt; Display Options &gt; Advanced button &gt; Series tab</b>
<b>See also</b>	<ul style="list-style-type: none"> <li>• <a href="#">"Display Options Dialog Box" on page 1378</a></li> <li>• <a href="#">"Editing Main Chart Dialog Box (Display Options Dialog Box)" on page 1380</a></li> <li>• <a href="#">"Chart Tab (Editing MainChart Dialog Box)" on page 1381</a></li> </ul>

User interface elements are described below:

UI Element	Description
<b>Format tab</b>	Set the border color, line color, pattern, and invert property for the lines or bars in your graph.
<b>Point tab</b>	Set the size, color, and shape of the points that appear within your line graph.
<b>General tab</b>	Select the type of cursor, the format of the axis values, and show/hide settings for the horizontal and vertical axes.
<b>Marks tab</b>	Configure the format for each point in the graph.

## Legend Window

This window enables you to configure the color, scale, minimum, maximum, average, median, and standard deviation of each measurement appearing in the graph.



<b>To access</b>	<b>Analysis Window &gt; Legend window</b>
<b>Tip</b>	<p><b>Filtering:</b> To show only certain values, click the down arrow in the selected column and click <b>Custom</b>. The Custom Filter dialog box opens. For details, see <a href="#">"Custom Filter Dialog Box" on page 1404</a>.</p> <p><b>Sorting:</b> To sort the measurements by a specific metrics, select a column header once to display the measurements in ascending order. Click it again to display them in descending order.</p>
<b>See also</b>	<ul style="list-style-type: none"> <li>• <a href="#">"Measurement Description Dialog Box" on page 1386</a></li> <li>• <a href="#">"Measurement Options Dialog Box" on page 1387</a></li> </ul>

## Legend Toolbar

User interface elements are described below:

UI Element	Description
	<b>Show.</b> Displays the selected measurements in the graph.
	<b>Hide.</b> Hides the selected measurements in the graph.
	<b>Show only Selected.</b> Displays the highlighted measurement only.
	<b>Show All.</b> Displays all the available measurements in the graph.
	<b>Filter.</b> Filters the graph by the measurements selected in the Legend window. You can select multiple measurements. To clear the filter, select <b>View &gt; Clear Filter/Group By</b> .
	<b>Configure.</b> Opens the Measurement Options dialog box that enables you to configure measurement options (for example, set color and measurement scale). For more information, see " <a href="#">Measurement Options Dialog Box</a> " on page 1387.
	<b>Show Description.</b> Opens the Measurement Description dialog box that displays the name, monitor type, and description of the selected measurement. For more information, see " <a href="#">Measurement Description Dialog Box</a> " on page 1386.
	<b>Animate.</b> Displays the selected measurement as a flashing line.
	<b>Configure Columns.</b> Opens the Legend Columns Options dialog box that enables you to select the columns to display in the Legend window.
	<b>Copy Selection.</b> Copies the selected rows to the clipboard. You can paste the data in a text file or a spreadsheet.
	<b>Copy All.</b> Copies all of the legend data to the clipboard, regardless of what is selected. You can paste the data in a text file or a spreadsheet.
	<b>Export.</b> Saves the legend data to a CSV file.

UI Element	Description
<b>&lt;Custom filter&gt;</b>	After adding a custom filter (by expanding the down arrow in the column headers), the window shows them at the bottom of the legend. Click the <b>x</b> button to remove the filter, or clear the check box to disable it temporarily. For details, see " <a href="#">Custom Filter Dialog Box</a> " on page 1404.
<b>Customize</b>	Opens the Filter Builder and allows you to save your filter settings to a file.

### Legend grid shortcut menu


User interface elements are described below:

UI Element	Description
<b>Show</b>	Displays the selected measurements in the graph.
<b>Hide</b>	Hides the selected measurements in the graph.
<b>Show only Selected</b>	Displays the highlighted measurement only.
<b>Show All</b>	Displays all the available measurements in the graph.
<b>Filter</b>	Filters the graph by the measurements selected in the Legend window. You can select multiple measurements. To clear the filter, select <b>View &gt; Clear Filter/Group By</b> .
<b>Configure</b>	Opens the Measurement Options dialog box that enables you to configure measurement options (for example, set color and measurement scale). For more information, see " <a href="#">Measurement Options Dialog Box</a> " on page 1387.
<b>Show Description</b>	Opens the Measurement Description dialog box that displays the name, monitor type, and description of the selected measurement. For more information, see " <a href="#">Measurement Description Dialog Box</a> " on the next page.
<b>Animate</b>	Displays the selected measurement as a flashing line.
<b>Auto Correlate</b>	Opens the Auto Correlate dialog box that enables you to correlate the selected measurement with other monitor measurements in the load test scenario. For more information on auto correlation, see " <a href="#">Auto Correlating Measurements</a> " on page 1416.

UI Element	Description
Configure Columns	Opens the Legend Columns Options dialog box that enables you to select the columns to display in the Legend window.
Web Page Diagnostics for <selected measurement>	Displays a Web Page Diagnostics graph for the selected transaction measurement (only available for the Average Transaction Response Time and Transaction Performance Summary graphs).
Break down	Displays a graph with a breakdown of the selected page (only available for the Web Page Diagnostics graphs).

## Measurement Description Dialog Box

This dialog box shows you additional information about the selected measurement.



To access	Legend Toolbar >
See also	<ul style="list-style-type: none"><li>• <a href="#">"Legend Window" on page 1383</a></li><li>• <a href="#">"Measurement Options Dialog Box" on the next page</a></li></ul>


User interface elements are described below:

UI Element	Description
Measurement	Displays the name of the selected measurement. Click the drop-down arrow to select a different measurement.

UI Element	Description
<b>Monitor Type</b>	Displays the type of monitor used to obtain the selected measurement.
<b>Description</b>	Displays a description of the selected monitored measurement.
<b>SQL</b>	If an SQL logical name is in use, displays the full SQL statement.

## ***Measurement Options Dialog Box***

This dialog box enables you to set the color and the scale for any measurement of the graph you selected.



<b>To access</b>	Legend Toolbar >
<b>See also</b>	<ul style="list-style-type: none"><li>• "Legend Window" on page 1383</li><li>• "Measurement Description Dialog Box" on the previous page</li></ul>


User interface elements are described below:

UI Element	Description
<b>Measurement</b>	Select a measurement to configure.
<b>Change Color</b>	Select a new color for the selected measurement.

UI Element	Description
Scale	Select the desired scale option: <ul style="list-style-type: none"><li>Set measurement scale to x. Select the scale with which you want to view the selected measurement.</li><li>Set automatic scale for all measurements. Uses an automatic scale optimized to display each measurement in the graph.</li><li>Set scale 1 for all measurements. Sets the scale to one for all measurements in the graph.</li><li>View measurement trends for all measurements. Standardizes the y-axis values in the graph, according to the following formula: New Y value = (Previous Y Value - Average of previous values) / STD of previous values.</li></ul>

## ***Legend Columns Options Dialog Box***

This dialog box enables you to select the columns to be displayed.




To access	<b>View &gt; Legend Columns</b>
See also	<a href="#">"Legend Window" on page 1383</a>

User interface elements are described below:

UI Element	Description
<b>Available Columns</b>	<p>Select or deselect the check boxes to the left of the column names to show or hide the columns respectively.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>The Color, Scale, and Measurement columns are mandatory and cannot be deselected.</li> <li>To rearrange the order in which the columns appear (from left to right), you use the vertical arrows to the right of the Available Columns list to place the columns in the desired order.</li> </ul>

## Apply/Edit Template Dialog Box

This dialog box enables you to configure template settings and select report template options. Using this dialog box, you can create new templates, open existing ones, and set the default template for your sessions.



To access

Tools > Templates

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Templates</b>	<p>Select one of the following buttons:</p> <ul style="list-style-type: none"> <li>•  Browse for a template.</li> <li>•  Add a new template. Enter the title of the new template in the <b>Add new template</b> dialog box.</li> <li>•  Duplicate the selected template.</li> <li>•  Delete the selected template.</li> <li>•  Set the selected template as the default.</li> </ul>
<b>Use automatic granularity</b>	<p>Applies the default Analysis granularity (one second) to the template. For information about setting Analysis granularity, see "<a href="#">"Changing the Granularity of the Data" on page 1414</a>.</p>
<b>Generate the following automatic HTML report</b>	<p>Generates an HTML report using the template. Specify or select a report name. For information about generating HTML reports, see "<a href="#">"HTML Report" on page 1649</a>.</p>
<b>Open html report after creation</b>	<p>If you selected the option of generating an automatic HTML report, select this option to automatically open the HTML report after it is created.</p>
<b>Automatically save the session as</b>	<p>Automatically saves the session using the template you specify. Specify or select a file name.</p>
<b>Automatically analyze the top problematic transactions</b>	<p>Automatically generates Transaction Analysis reports for the transactions with the worst SLA violations. Reports are generated for a maximum of five transactions. For more information about Transaction Analysis reports, see "<a href="#">"Analyze Transactions Dialog Box" on page 1634</a>.</p>
<b>Automatically close Analysis after saving session</b>	<p>Automatically closes Analysis after a session is automatically saved (using the previous option). This prevents the running of multiple instances of Analysis.</p>
<b>Generate the following automatic Rich Reports</b>	<p>The selected reports are added to the template.</p>

UI Element	Description
<check box on left of Template's Name>	Select to add report template to selected template. The reports are added to the session.
<b>Word</b>	Generates a report using the selected report template to MS Word. <b>Note:</b> Take into account that the content load may affect the table format within the MS Word document.
<b>Excel</b>	Generates a report using the selected report template to Excel.
<b>PDF</b>	Generates a report using the selected report template to PDF.
<b>HTML</b>	Generates a report using the selected report template to HTML.
<b>Graphs tab</b>	Displays the list of graphs that are included in the template. When the template is applied to a session, the graphs are displayed under Graphs in Session Explorer. If there is no data in the session, the graphs are not created.
<b>Apply to Session</b>	Applies your changes to the current analysis session without closing the dialog box.

## Color Palettes

Color Palettes allow you to define the colors that will be used in Analysis graphs and to allocate those colors to specific series. There is a general, default palette and you can also define a Color Palette for a specific session. You can add new colors to a palette and delete existing colors from a palette, but a palette must contain at least thirty two colors.


When a new session is created, or when you open an existing session that does not have a Graph Colors file, Analysis uses the general color palette. When you open an existing session that has a Graph Colors file, Analysis uses the file from the session folder.


The colors are allocated to the graph in the order they appear in the palette. Colors allocated to a series, are used to represent graph elements for the series in the order the colors were allocated. To change the colors in the graph, update the palette, close and re-open the graph.

For more information, see "[Color Palette Dialog Box](#)" below.

## Color Palette Dialog Box

This dialog box enables you to configure the colors that will be used in graphs. You use the General Color Palette to define a default set of colors for all graphs and the Session Color Palette to define the set of colors for a specific session.





<b>To access</b>	<ul style="list-style-type: none"><li>• Tools &gt; General Color Palette</li><li>• Tools &gt; Session Color Palette</li></ul>
<b>See also</b>	<a href="#">"Color Palettes" on page 1391</a>

User interface elements are described below:

UI Elements>	Description
<b>Return to default</b>	Restores the palette to the currently saved General Palette.  <b>Note:</b> This button appears on the General Color Palette, not on the Session Color Palette.
<b>Apply default palette</b>	Applies the default palette as the session palette.  <b>Note:</b> This button appears on the Session Color Palette, not on the General Color Palette.
<b>Colors tab</b>	Allows you to configure the colors on the palette.

UI Elements>	Description
	Add a new color to the palette.
	Replace an existing color with a new color.
	Delete a color from the palette.
	Move the color upwards.
	Move the color downwards.
<b>Series tab - left pane</b>	Allows you to configure the series on the palette.
	Add a new series to the palette.
	Edit a series.
	Delete a series from the palette.
	Move the series upwards.
	Move the series downwards.
<b>Series tab - right pane</b>	Allows you to define colors for the selected series.
	Add a color to the series.
	Delete a color from the series.
	Move the color upwards.
	Move the color downwards.

## Filtering and Sorting Graph Data

### ***Filtering Graph Data Overview***

You can filter graph data to show fewer transactions for a specific segment of the load test scenario. More specifically, you can display four transactions beginning from five minutes into the scenario and ending three minutes before the end of the scenario.

You can filter for a single graph, in all graphs in a load test scenario, or in the summary graph.

The available filter conditions differ for each type of graph. The filter conditions also depend on your scenario. For example, if you only had one group or one load generator machine in your scenario, the Group Name and Load Generator Name filter conditions do not apply.

**Note:** You can also filter merged graphs. The filter conditions for each graph are displayed on separate tabs.

## Sorting Graph Data Overview

You can sort graph data to show the data in more relevant ways. For example, Transaction graphs can be grouped by the Transaction End Status, and Vuser graphs can be grouped by Scenario Elapsed Time, Vuser End Status, Vuser Status, and Vuser ID.

You can sort by one or several groups—for example by Vuser ID and then Vuser status. The results are displayed in the order in which the groups are listed. You can change the grouping order by rearranging the list.

## Filter Conditions

### Common Filter Condition Options

The following filter conditions are common to many graphs:

Filter Condition	Filters the graph according to...
Host Name	The name of the Host machine. Select one or more hosts from the drop-down list.
Transaction End Status	The end status of a transaction: <i>pass</i> , <i>fail</i> , <i>stop</i> .
Scenario Elapsed Time	The time that elapsed from the beginning to the end of the load test scenario. For more information about setting the time range, see " <a href="#">"Scenario Elapsed Time Dialog Box" on page 1409</a> ".
Vuser ID	The Vuser ID. For more information, see " <a href="#">"Vuser ID Dialog Box" on page 1410</a> ".
Script Name	The name of the script.
Group Name	The name of the group to filter by.
Think Time	The Think Time option in the graph filter for complete mode is turned off by default. The transaction time displayed shows pure time.

### Vuser Graphs

You can apply the following filter conditions to Vuser graphs:

Filter Condition	Filters the graph according to...
<b>Vuser Status</b>	The Vuser status: <i>load, pause, quit, ready, run</i>
<b>Vuser End Status</b>	The status of the Vuser at the end of the transaction: <i>error, failed, passed, stopped</i> .
<b>Number of Released Vusers</b>	The number of Vusers that were released.
<b>Rendezvous Name</b>	The name of the rendezvous point.

## Error Graphs

You can apply the following filter conditions to Error graphs:

Filter Condition	Filters the graph according to...
<b>Error Type</b>	The type of error (per error number).
<b>Parent Transaction</b>	The parent transaction.
<b>Line Number in Script</b>	The line number in the script.

## Transaction Graphs

You can apply the following filter conditions to Transaction graphs:

Filter Condition	Filters the graph according to...
<b>Transaction Name</b>	The name of the transaction.
<b>Transaction Response Time</b>	The response time of the transaction.
<b>Transaction Hierarchical Path</b>	The hierarchical path of the transaction. For more information on setting this condition, see " <a href="#">Hierarchical Path Dialog Box</a> " on page 1408.

## Web Resource Graphs

You can apply the following filter conditions to Web Resources graphs:

Filter Condition	Filters the graph according to...
<b>Web Resource Name</b>	The name of the Web resource.
<b>Web Resource Value</b>	The value of the Web resource.
<b>Web Server Resource Name</b>	The name of the Web Server resource.
<b>Web Server Resource Value</b>	The value of the Web Server resource.

## Web Page Diagnostics Graphs

You can apply the following filter conditions to Web Page Diagnostics graphs:

Filter Condition	Filters the graph according to...
<b>Component Name</b>	The name of the component.
<b>Component Response Time</b>	The response time of the component.
<b>Component DNS Resolution Time</b>	The amount of time the component needs to resolve the DNS name to an IP address, using the closest DNS server.
<b>Component Connection Time</b>	The time taken for the component to establish an initial connection with the Web server hosting the specified URL.
<b>Component First Buffer Time</b>	The time that passes from the component's initial HTTP request (usually GET) until the first buffer is successfully received back from the Web server.
<b>Component Receive Time</b>	The time that passes until the component's last byte arrives from the server and the downloading is complete.
<b>Component SSL Handshaking Time</b>	The time take for the component to establish an SSL connection. (Applicable to HTTPS communication only.)
<b>Component FTP Authentication Time</b>	The time taken for the component to authenticate the client. (Applicable to FTP protocol communication only).
<b>Component Error Time</b>	The average amount of time that passes from the moment a component's HTTP request is sent until the moment an error message (HTTP errors only) is returned.
<b>Component Size (KB)</b>	The size of the component (in kilobytes).
<b>Component Type</b>	The type of component: <i>Application; Image; Page; Text</i>
<b>Component Hierarchical Path</b>	The hierarchical path of the component. For more information on setting this condition, see " <a href="#">Hierarchical Path Dialog Box</a> " on page 1408.
<b>Component Network Time</b>	The amount of time from the component's first HTTP request, until receipt of ACK.

Filter Condition	Filters the graph according to...
<b>Component Server Time</b>	The amount of time from when the component receives of ACK, until the first buffer is successfully received back from the Web server.
<b>Component Client Time</b>	The average amount of time that passes while a component request is delayed on the client machine due to browser think time or other client-related delays.

## User Defined Data Point Graphs

You can apply the following filter conditions to User-Defined Data Point graphs:

Filter Condition	Filters the graph according to...
<b>Datapoint Name</b>	The name of the data point.
<b>Datapoint Value</b>	The value of the data point.

## System Resources Graphs

You can apply the following filter conditions to System Resource graphs:

Filter Condition	Filters the graph according to...
<b>System Resource Name</b>	The name of the system resource.
<b>System Resource Value</b>	The value of the system resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Network Monitor Graphs

You can apply the following filter conditions to Network Monitor graphs:

Filter Condition	Filters the graph according to...
<b>Network Path Name</b>	The name of the network path.
<b>Network Path Delay</b>	The delay of the network path.
<b>Network Path Father</b>	The father of the network path.
<b>Network SubPath Name</b>	The name of the network subpath.
<b>Network SubPath Delay</b>	The delay of the network subpath.
<b>Network Full Path</b>	The full network path.
<b>Network Segment Name</b>	The name of the network segment.
<b>Network Segment Delay</b>	The delay of the network segment.
<b>Network Segment Full Path</b>	The full network segment path.

## Firewall Graphs

You can apply the following filter conditions to Firewall graphs:

Filter Condition	Filters the graph according to...
<b>Firewall Resource Name</b>	The name of the Firewall resource.
<b>Firewall Resource Value</b>	The value of the firewall resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Web Server Resource Graphs

You can apply the following filter conditions to Web Server Resource graphs:

Filter Condition	Filters the graph according to...
<b>Measurement Name</b>	The name of the measurement.
<b>Measurement Value</b>	The measurement value. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Web Application Server Resource Graphs

You can apply the following filter conditions to Web Application Server Resource graphs:

Filter Condition	Filters the graph according to...
<b>Resource Name</b>	The name of the resource.
<b>Resource Value</b>	The value of the resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Database Server Resource Graphs

You can apply the following filter conditions to Database Server Resource graphs:

Filter Condition	Filters the graph according to...
<b>Database Resource Name</b>	The name of the database resource.
<b>Database Resource Value</b>	The value of the database resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Streaming Media Graphs

You can apply the following filter conditions to Streaming Media graphs:

Filter Condition	Filters the graph according to...
<b>Streaming Media Name</b>	The name of the streaming media.
<b>Streaming Media Value</b>	The value of the streaming media. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## ERP/CRM Server Resource Graphs

You can apply the following filter conditions to ERP/CRM Server Resource graphs:

Filter Condition	Filters the graph according to...
<b>ERP/CRM Server Resource Name</b>	The name of the ERP/CRM server resource.
<b>ERP/CRM Server Resource Value</b>	The value of the ERP/CRM Server resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.
<b>ERP Server Resource Name</b>	The name of the ERP server resource.
<b>ERP Server Resource Value</b>	The value of the ERP server resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Siebel Diagnostics Graphs

You can apply the following filter conditions to Siebel Diagnostics graphs:

Filter Condition	Filters the graph according to...
<b>Siebel Transaction Name</b>	The name of the Siebel transaction.
<b>Siebel Request Name</b>	The name of the Siebel request.
<b>Siebel Layer Name</b>	The name of the Siebel layer.
<b>Siebel Area Name</b>	The name of the Siebel area.
<b>Siebel Sub-Area Name</b>	The name of the Siebel sub-area.
<b>Siebel Server Name</b>	The name of the Siebel server.
<b>Siebel Script Name</b>	The name of the Siebel script.
<b>Response Time</b>	The response time of the Siebel transaction.
<b>Siebel Chain of Calls</b>	The chain of calls for the Siebel transaction.

## Siebel DB Diagnostics Graphs

You can apply the following filter conditions to Siebel DB Diagnostics graphs:

Filter Condition	Filters the graph according to...
<b>Transaction Name - SIEBEL</b>	The name of the Siebel DB transaction.
<b>SQL Chain of Calls</b>	The SQL chain of calls for the Siebel DB transaction.
<b>SQL Alias Name</b>	The SQL alias name for the Siebel DB transaction.
<b>SQL Response Time</b>	The SQL response time of the Siebel DB transaction.

## Oracle 11i Diagnostics Graphs

You can apply the following filter conditions to Oracle 11i Diagnostics graphs:

Filter Condition	Filters the graph according to...
<b>Transaction Name - ORACLE</b>	The name of the Oracle transaction.
<b>SQL Chain of Calls</b>	The SQL chain of calls for the Oracle transaction.
<b>SQL Alias Name - Oracle</b>	The SQL alias name for the Oracle transaction.
<b>SQL Response Time</b>	The SQL response time of the Oracle transaction.
<b>Oracle SQL Parse Time</b>	The SQL parse time of the Oracle transaction.
<b>Oracle SQL Execute Time</b>	The SQL execute time of the Oracle transaction.
<b>Oracle SQL Fetch Time</b>	The SQL fetch time of the Oracle transaction.
<b>Oracle SQL Other Time</b>	Other SQL time for the Oracle transaction.

## Java Performance Graphs

You can apply the following filter conditions to Java Performance graphs:

Filter Condition	Filters the graph according to...
<b>Java Performance Resource Name</b>	The name of the Java performance resource.
<b>Java Performance Resource Value</b>	The value of the Java performance resource.

## J2EE & .NET Diagnostics Graphs

You can apply the following filter conditions to J2EE & .NET Diagnostics graphs:

Filter Condition	Filters the graph according to...
<b>Transaction Name</b>	The name of the Java transaction.

Filter Condition	Filters the graph according to...
<b>Method Chain of Calls</b>	The chain of calls for the Java method.
<b>Layer Name</b>	The name of the layer.
<b>Class Name</b>	The name of the class.
<b>Method Name</b>	The name of the method.
<b>SQL Logical Name</b>	The SQL logical name for the Java transaction.
<b>Response Time</b>	The response time of the Java transaction.
<b>Host Name - J2EE/.NET</b>	The name of the host for the J2EE & .NET transaction.
<b>Application Host Name - (VM)</b>	The name of the application host for the VM.
<b>Transaction Request</b>	The request for the transaction.
<b>Transaction Hierarchical Path</b>	The hierarchical path of the transaction. For more information on setting this condition, see " <a href="#">Hierarchical Path Dialog Box</a> " on page 1408.

## Application Component Graphs

You can apply the following filter conditions to Application Component graphs:

Filter Condition	Filters the graph according to...
<b>Component Resource Name</b>	The resource name of the component.
<b>Component Resource Value</b>	The value of the component resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.
<b>COM+ Interface</b>	The interface of the COM+ component.
<b>COM+ Response Time</b>	The response time of the COM+ component.
<b>COM+ Call Count</b>	The call count of the COM+ component.
<b>COM+ Method</b>	The method of the COM+ component.

Filter Condition	Filters the graph according to...
.NET Resource Name	The resource name of the .NET component.
.NET Value	The .NET resource value. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.
.NET Class	The class of the .NET component.
.NET Response Time	The response time of the .NET component.
.NET Call Count	The call count of the .NET component.
.NET Method	The method of the .NET component.

## Application Deployment Graphs

You can apply the following filter conditions to Application Deployment graphs:

Filter Condition	Filters the graph according to...
Citrix Resource Name	The name of the Citrix resource.
Citrix Resource Value	The value of the Citrix resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Middleware Performance Graphs

You can apply the following filter conditions to Middleware Performance graphs:

Filter Condition	Filters the graph according to...
Message Queue Resource Name	The name of the message queue resource.
Message Queue Resource Value	The value of the Message Queue resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Infrastructure Resource Graphs

You can apply the following filter conditions to Infrastructure Resource graphs:

Filter Condition	Filters the graph according to...
Network Client	The name of the network client.
Network Client Value	The value of the network client. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.


## External Monitor Graphs

You can apply the following filter conditions to External Monitor graphs:

Filter Condition	Filters the graph according to...
<b>External Monitor Resource Name</b>	The name of the external monitor resource.
<b>External Monitor Resource Value</b>	The value of the external monitor resource. See " <a href="#">Set Dimension Information Dialog Box</a> " on page 1409.

## Custom Filter Dialog Box

This dialog box enables you to customize your filter criteria.



<b>To access</b>	Do the following: <ol style="list-style-type: none"><li>1. In a <b>Legend</b> window, click a column header.</li><li>2. Expand the down arrow and choose <b>(Custom)</b>.</li></ol>
<b>Tip</b>	You can use wildcards: <ul style="list-style-type: none"><li>• Use <u>_</u> to represent a single character.</li><li>• Use <u>%</u> to represent a series of characters.</li></ul>
<b>See also</b>	<a href="#">"Legend Window" on page 1383</a>

User interface elements are described below:

UI Element	Description
<b>&lt;First Evaluator Expression&gt;</b>	A drop-down list of evaluation expressions such as <b>equals</b> , <b>is greater than</b> , <b>like</b> , and so forth, followed by a value.
<b>Operator</b>	The logical operator by which to add a second expression: <b>AND</b> or <b>OR</b> .

UI Element	Description
<Second Evaluator Expression>	A drop-down list of evaluation expressions such as <b>equals</b> , <b>is greater than</b> , <b>like</b> , and so forth, followed by a value.

For example, the above image shows how to filter the data for transactions that begin with the phrase "Action\_Transaction", using **Like** and **Action\_Transaction%**.

After you save a customization for one of the metrics, the Analysis displays it in the lower section of the Legend window.

## Filter Dialog Boxes


The filter dialog boxes (Graph Settings, Global Filter, and Analysis Summary Filter) enable you to filter the data that is displayed in the graph or report.

When adding a graph, the filter and sort button is displayed which enables you to filter and sort data before the graph is displayed.

To access	Use one of the following:
	<ul style="list-style-type: none"><li>• View &gt; Set Filter/Group By or click </li><li>• File &gt; Set Global Filter or click </li><li>• View &gt; Summary Filter or click </li></ul>
<b>Note</b>	Some of the following fields are not displayed in all of the filter boxes.

User interface elements are described below:

UI Element	Description
<b>Filter Condition</b>	Select criteria and values for each filter condition that you want to employ. The applicable filter conditions are displayed for each graph. For details on each graphs filter conditions, see the chapter on the relevant graph.
<b>Criteria</b>	Select "=" (equals) or "<>" (does not equal).

UI Element	Description
<b>Values</b>	<p>The filter conditions are grouped into three value types (discrete, continuous, and time-based).</p> <p>A discrete value is a distinct integer (whole number) or string value such as Transaction Name or Vuser ID. Select the check box(es) of the value(s) that you want to include in your filter. You can also customize your filter by entering wild cards to depict any single character or any series of characters.</p>  <ul style="list-style-type: none"> <li>• A continuous value is a variable dimension that can take any value within the minimum and maximum range limits, such as Transaction Response Time. You set the dimension information for each measurement in the <a href="#">"Set Dimension Information Dialog Box" on page 1409</a>.</li> <li>• A time-based value is a value that is based on time relative to the start of the load test scenario. Scenario Elapsed Time is the only condition that uses time-based values. You specify time-based values in the <a href="#">"Scenario Elapsed Time Dialog Box" on page 1409</a>.</li> </ul> <p>For some filter conditions, one of the following dialog boxes opens to enable you to specify additional filtering details:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Set Dimension Information Dialog Box" on page 1409</a></li> <li>• <a href="#">"Vuser ID Dialog Box" on page 1410</a></li> <li>• <a href="#">"Scenario Elapsed Time Dialog Box" on page 1409</a></li> <li>• <a href="#">"Hierarchical Path Dialog Box" on page 1408</a>: Enables you to display the hierarchical path of a transaction or component, or a method chain of calls.</li> </ul>
<b>Transaction Percentile</b>	<p>The Summary Report contains a percentile column showing the response time of 90% of transactions (90% of transactions that fall within this amount of time). To change the value of the default 90 percentile, enter a new figure in the <b>Transaction Percentile</b> box.</p>
<b>Set Default</b>	<p>Displays the default criteria and values for each filter condition.</p>
<b>Clear All</b>	<p>Deletes all of the information you entered in the dialog box.</p>

UI Element	Description
<b>Group By settings</b>	<p>Use these settings to sort the graph display by grouping the data. You can group the data by:</p> <ul style="list-style-type: none"><li>• <b>Available groups.</b> Select the group by which you want to sort the results, and click the right arrow.</li><li>• <b>Selected groups.</b> Displays a list of all the selected groups by which the results will be sorted. To remove a value, select it and click the left arrow.</li></ul>
<b>Reset all graphs to their defaults prior to applying the Global Filter</b>	All graphs filter settings are reverted to their default.

## Filter Builder Dialog Box

The Filter Builder dialog box enable you to design, add, and edit filters for your graph.

<b>To access</b>	<b>Use one of the following:</b> <ol style="list-style-type: none"><li>1. In the Legend pane, expand the down arrow in a column header.</li><li>2. Select <b>Custom</b> to open the Custom Filter dialog box. Provide filter details and click OK.</li><li>3. Click <b>Customize</b> in the filter entry in the lower part of the <b>Legend</b> pane.</li></ol>
<b>See also</b>	<a href="#">"Custom Filter Dialog Box" on page 1404</a>


User interface elements are described below:

UI Element	Description
<b>Filter button</b>	Opens a menu with the following options: <ul style="list-style-type: none"><li>• <b>Add Condition.</b> Add another condition for the current filter.</li><li>• <b>Add Group.</b> Adds a second condition, joined by a logical operator AND or OR, to the last condition in the list.</li><li>• <b>Clear All.</b> Removes all of the conditions in the window.</li></ul>

UI Element	Description
<input type="checkbox"/>	Opens a menu with the following options: <ul style="list-style-type: none"><li>• <b>Add Condition.</b> Add another condition for the current filter.</li><li>• <b>Add Group.</b> Adds a second condition, joined by a logical operator AND or OR, to the selected condition in the list.</li><li>• <b>Remove Row.</b> Removes the selected condition.</li></ul>
<b>Open</b>	Opens an .flt file saved from a previous session.
<b>Save as</b>	Saves all of the conditions to an .flt file.

## Hierarchical Path Dialog Box

This dialog box enables you to display the hierarchical path of a transaction or component, or a method chain of calls.




To access	View menu > Set Filter/Group by > Filter condition pane > <b>Transaction, Component Hierarchical Path or a method chain of calls</b>
-----------	--------------------------------------------------------------------------------------------------------------------------------------

User interface elements are described below:

UI Element	Description
<b>Transaction, Component Hierarchical Path or a method chain of calls</b>	Select the box for the path where you want to start to see results. Only the selected path and its immediate sub-nodes will be displayed.

## Scenario Elapsed Time Dialog Box

This dialog box enables you to specify the start and end time range for the graph's x-axis.




To access	<b>View menu &gt; Set Filter/Group by &gt; Filter condition pane &gt; Scenario Elapsed Time</b>
Note	The time is relative to the start of the scenario.

User interface elements are described below:

UI Element	Description
From	Specify a start value for the desired range.
To	Specify an end value for the desired range.

## Set Dimension Information Dialog Box

This dialog box enables you to set the dimension information for each measurement (transaction, number of released Vusers, resource) in the result set. You specify the minimum and maximum values for each measurement you want in the analysis. By default, the full range of values for each measurement is displayed.




To access	You can open this dialog box from the following locations: <ul style="list-style-type: none"><li>• <b>Transaction graphs &gt; View menu &gt; Set Filter/Group by &gt; Filter condition pane &gt; Transaction Response Time</b></li><li>• <b>Vusers graph &gt; Rendezvous graph &gt; View menu &gt; Set Filter/Group by &gt; Filter condition pane &gt; Number of Released Vusers</b></li><li>• All graphs that measure resources (<b>Web Server, Database Server, and so on</b>) &gt; <b>View menu &gt; Set Filter/Group by &gt; Filter condition pane &gt; Resource Value</b></li></ul>
Note	If you are specifying the start and end time for a transaction (in minutes:seconds format), the time is relative to the beginning of the load test scenario.

User interface elements are described below:

UI Element	Description
<b>Minimum</b>	Specify a minimum value for the measurement.
<b>Maximum</b>	Specify a maximum value for the measurement.

## Vuser ID Dialog Box

This dialog box opens to enable the entering of additional filter information for the Vuser ID filter condition.



**To access** View menu > Set Filter/Group by > Filter condition pane > Vuser ID

User interface elements are described below:


UI Element	Description
<b>Value</b>	Enter the Vuser IDs of the Vusers you want the graph(s) to display, separated by commas.
<b>Range</b>	Specify the beginning and end of the desired range of Vusers you want the graph(s) to display.
<b>Cross Vuser</b>	Cross Vuser transactions are transactions that start with one Vuser and end with a different Vuser, such as sending an email. Selecting this check box places the value "CrossVuser" in the Vuser ID filter. By default, the check box is not selected.  <b>Note:</b> Only transaction graphs have Cross Vuser data.
<b>Vusers</b>	Displays the existing Vuser IDs from which you can choose.

## Working with Analysis Graph Data

Analysis contains several utilities that enable you to manage graph data to most effectively view the displayed data.

## Determining a Point's Coordinates

You can determine the coordinates and values at any point in a graph. Place the cursor over the point you want to evaluate and Analysis displays the axis values and other grouping information.




## Drilling Down in a Graph


*Drill down* enables you to focus on a specific measurement within your graph and display it according to a desired grouping. The available groupings depend on the graph. For example, the Average Transaction Response Time graph shows one line per transaction. To determine the response time for each Vuser, you drill down on one transaction and sort it according to Vuser ID. The graph displays a separate line for each Vuser's transaction response time.

**Note:** The drill down feature is not available for the Web Page Diagnostics graph.

The following graph shows a line for each of five transactions.



When you drill down on the MainPage transaction, grouped by Vuser ID, the graph displays the response time only for the MainPage transaction, one line per Vuser.



You can see from the graph that the response time was longer for some Vusers than for others.


To determine the response time for each host, you drill down on one transaction and sort it according to host. The graph displays a separate line for the transaction response time on each host. For more information on drilling down in a graph, see ["How to Manage Graph Data" on page 1417](#).

## ***Changing the Granularity of the Data***

You can make the graphs easier to read and analyze by changing the granularity (scale) of the *x-axis*. The maximum granularity is half of the graph's time range. To ensure readability and clarity, Analysis automatically adjusts the minimum granularity of graphs with ranges of 500 seconds or more.

In the following example, the Hits per Second graph is displayed using different granularities. The y-axis represents the number of hits per second within the granularity interval. For a granularity of 1, the y-axis shows the number of hits per second for each one second period of the load test scenario.

For a granularity of 5, the y-axis shows the number of hits per second for every five-second period of the scenario.



In the above graphs, the same load test scenario results are displayed in a granularity of 1, 5, and 10. The lower the granularity, the more detailed the results. For example, using a low granularity as in the upper graph, you see the intervals in which no hits occurred. It is useful to use a higher granularity to study the overall Vuser behavior throughout the scenario.

By viewing the same graph with a higher granularity, you can see that overall, there was an average of approximately 1 hit per second.

## ***Viewing Measurement Trends***

You can view the pattern of a line graph more effectively by standardizing the graph's y-axis values. Standardizing a graph causes the graph's y-axis values to converge around zero. This cancels the

measurements' actual values and allows you to focus on the behavior pattern of the graph during the course of the load test scenario.


Analysis standardizes the y-axis values in a graph according to the following formula:

New Y value = (Previous Y Value - Average of previous values) / STD of previous values

## Auto Correlating Measurements

You can detect similar trends among measurements by correlating a measurement in one graph with measurements in other graphs. Correlation cancels the measurements' actual values and allows you to focus on the behavior pattern of the measurements during a specified time range of the load test scenario.

In the following example, the **t106Zoek:245.Irr** measurement in the Average Transaction Response Time graph is correlated with the measurements in the Windows Resources, Microsoft IIS, and SQL Server graphs. The five measurements most closely correlated with **t106Zoek:245.Irr** are displayed in the graph below.



**Note:** This feature can be applied to all line graphs except the Web Page Diagnostics graph.

## **Viewing Raw Data**

You can view the actual raw data collected during test execution for the active graph. The Raw Data view is not available for all graphs.

Viewing the raw data can be especially useful in the following cases:

- To determine specific details about a peak—for example, which Vuser was running the transaction that caused the peak value(s).
- To perform a complete export of unprocessed data for your own spreadsheet application.

For user interface details, click "[Graph/Raw Data View Table](#)" on page 1423.

## **How to Manage Graph Data**

The following list includes the utilities you can use in Analysis to enable you to manage graph data to most effectively view the displayed data.

### **Determine a point's coordinates**

To determine the coordinates and values at any point in a graph, place the cursor over the point you want to evaluate. Analysis displays the axis values and other grouping information.

### **Drill down in a graph**

Drill down enables you to focus on a specific measurement within your graph and display it according to the desired grouping.

1. Right-click on a line, bar, or segment within the graph, and select **Drill Down**. The **Drill Down Options** dialog box opens, listing all of the measurements in the graph.
2. Select a measurement for drill down.
3. From the **Group By** box, select a group by which to sort.
4. Click **OK**. Analysis drills down and displays the new graph.

To undo the last drill down settings, choose **Undo Set Filter/Group By** from the right-click menu.

- To perform additional drill-downs, repeat steps 1 to 4.
- To clear all filter and drill down settings, choose **Clear Filter/Group By** from the right-click menu.

### **Filter the data**

This task describes how to filter the data and create custom filters.

1. In the Legend window, click the column header of the measurement you want to use as a base for the filter.
2. To show a single entry, expand the drop-down list and select that entry.
3. To create a custom filter, select **Custom** in the drop-down list. The Custom Filter dialog box opens.
4. Select an evaluation expression and provide a value. To use wildcards, use an underscore, \_, to represent a single character and % for multiple characters. For details, see "["Custom Filter Dialog Box" on page 1404](#)".
5. To provide additional criteria, select a logical operator, **AND** or **OR** and set up the second expression.

## Change the granularity of the data

This task describes how to change the granularity of a graph.

1. Click inside a graph.
2. Select **View > Set Granularity**, or click the **Set Granularity** button . The Granularity dialog box opens.
3. Enter the granularity of the x-axis and select a time measurement. The maximum granularity is half of the graph's time range.
4. To ensure readability and clarity, LoadRunner automatically adjusts the minimum granularity of graphs with ranges of 500 seconds or more.
5. Click **OK**.

## View measurement trends

This task describes how to activate the View Measurements Trends option from a line graph.

1. Select **View > View Measurement Trends**, or right-click the graph and choose **View Measurement Trends**. Alternatively, you can select **View > Configure Measurements** and check the View measurement trends for all measurements box.

**Note:** The standardization feature can be applied to all line graphs except the Web Page Diagnostics graph.

2. View the standardized values for the line graph you selected. The values in the Minimum, Average, Maximum, and Std. Deviation legend columns are real values.

To undo the standardization of a graph, repeat step 1.

**Note:** If you standardize two line graphs, the two y-axes merge into one y-axis.

## Auto correlate measurements

You can detect similar trends among measurements by correlating a measurement in one graph with measurements in other graphs. Correlation cancels the measurements' actual values and allows you to focus on the behavior pattern of the measurements during a specified time range of the load test scenario.

1. From a graph or legend, right-click the measurement you want to correlate and choose **Auto Correlate**. The Auto Correlate dialog box opens with the selected measurement displayed in the graph.
2. Select a suggested time range method and time range.
3. If you applied a time filter to your graph, you can correlate values for the complete scenario time range by clicking the **Display** button in the upper right-hand corner of the dialog box.
4. To specify the graphs you want to correlate with a selected measurement and the type of graph output to be displayed, perform the following:
  - Select the **Correlation Options** tab.
  - Select the graphs to correlate, the data interval, and output options, as described in "[Drill Down Options Dialog Box](#)" below.
  - On the **Time Range** tab, click **OK**. Analysis generates the correlated graph you specified. Note the two new columns—**Correlation Match** and **Correlation**—that appear in the Legend window below the graph.

To specify another measurement to correlate, select the measurement from the Measurement to Correlate box at the top of the Auto Correlate dialog box.


The minimum time range should be more than 5% of the total time range of the measurement. Trends which are smaller than 5% of the whole measurement will be contained in other larger segments.

Sometimes, very strong changes in a measurement can hide smaller changes. In cases like these, only the strong change is suggested, and the **Next** button will be disabled.

**Note:** This feature can be applied to all line graphs except the Web Page Diagnostics graph.

## ***Drill Down Options Dialog Box***

This dialog box lists all the measurements in the graph.




To access	<Right-click> graph line/bar/segment > Drill Down
See also	<a href="#">"Drilling Down in a Graph" on page 1412</a>

User interface elements are described below:

UI Element	Description
Drill Down on	Filter graph by selected transaction.
Group By	The selected transaction is sorted by selected criteria.

## Auto Correlate Dialog Box

This dialog box enables you to configure settings used to correlate measurements from the selected graph with measurements in other graphs.



To access	Use one of the following; Right click on graph > <b>Auto Correlate</b> Right click on graph > <b>Auto Correlate &gt; Time Range</b> tab Right click on graph > <b>Auto Correlate &gt; Correlation Options</b> tab
Important information	You can also use the green and red vertical drag bars to specify the start and end values for the scenario time range.
Note	The granularity of the correlated measurements graph may differ from that of the original graph, depending on the scenario time range defined.
See also	<a href="#">"Auto Correlating Measurements" on page 1416</a>

## Time Range Tab

The Time Range tab of the Auto Correlate dialog box enables you to specify a load test scenario time range for the correlated measurement graph.

User interface elements are described below:

UI Element	Description
<b>Measurement to Correlate</b>	Select the measurement you want to correlate.
<b>Display values for complete time range</b>	Click <b>Display</b> to correlate values for the complete scenario time range. This option is available only if you applied a time filter to your graph.
<b>Suggest Time Range By</b>	Analysis automatically demarcates the most significant time period for the measurement in the scenario. <ul style="list-style-type: none"> <li>• <b>Trend.</b> Demarcated an extended time segment which contains the most significant changes.</li> <li>• <b>Feature.</b> Demarcates a smaller dimension segment which forms the trend.</li> </ul>
<b>Best</b>	Choose the time segment most dissimilar to its adjacent segments.
<b>Next</b>	Suggest the next time segment for auto correlation. Each suggestion is successively less dissimilar.
<b>Previous</b>	Return to the previous suggestion of a time segment.
<b>Automatically suggest for new measurement</b>	Generates new suggestions each time that the Measurement to Correlate item changes.
<b>From</b>	Specify a start value (in hh:mm:ss format) for the desired scenario time range.
<b>To</b>	Specify an end value (in hh:mm:ss format) for the desired scenario time range.

### Correlation Options tab

You use the Correlation Options tab of the Auto Correlate dialog box to set the graphs to correlate, the data interval, and the output options.


User interface elements are described below:

UI Element	Description
<b>Select Graphs for Correlation</b>	Select the graphs whose measurements you want to correlate with your selected measurement.

UI Element	Description
Data Interval	<p>Calculate the interval between correlation measurement polls.</p> <ul style="list-style-type: none"><li>• <b>Automatic.</b> Uses an automatic value, determined by the time range.</li><li>• <b>Correlate data based on X second intervals.</b> Enter a fixed value.</li></ul>
Output	<p>Choose the level of output displayed.</p> <ul style="list-style-type: none"><li>• <b>Show the X most closely correlated measurements.</b> Displays only the specified number of measurements most closely related to the selected measurement. The default value is 5.</li><li>• <b>Show measurements with an influence factor of at least X%.</b> Displays only those measurements that converge to the specified percent with the selected measurement. The default value is 50%.</li></ul>

## Graph/Raw Data View Table

You can view graph data in spreadsheet view or raw data view. The data is instantly displayed on request.




The screenshot shows a Windows application window titled "Graph Data". The window has a menu bar with "File", "Edit", "View", "Help", and a toolbar with icons for "New", "Open", "Save", and "Print". The main area is a table with two columns: "Relative Time" and "Run". The data rows are as follows:

Relative Time	Run
00:00	59
01:04	64
02:08	73
03:12	78
04:16	87
05:20	92
06:24	96
08:32	100
09:36	104
11:44	108
13:52	110
25:36	107
26:40	96
27:44	86
28:48	78
29:52	37
30:56	30
32:00	0
33:04	0


<b>To access</b>	Click the appropriate tab on the right border of the Analysis window or do one of the following: <ul style="list-style-type: none"><li>• <b>Windows &gt; Graph Data</b></li><li>• <b>Windows &gt; Raw Data</b></li></ul>
<b>Note</b>	Raw Data is not available for all graphs.

User interface elements are described below:

UI Element	Description
	Copies the data that you have selected.
	Copies the spreadsheet to the clipboard. You can paste to a spreadsheet.
	Saves the spreadsheet data to an Excel or CSV file. In Excel, you can generate your own customized graphs.
	Use the buttons on the toolbar to navigate through the table, and mark any records for future reference.
<b>Relative Time</b>	The first column in the Graph Data window. displays the elapsed scenario time (the x-axis values). The following columns displays the relative y-axis values for each measurement represented on the graph.
<b>Raw Data dialog box</b>	In <b>Set Range</b> , set a time range. 

## Graph Properties Window

This window displays the details of the graph or report selected in the Session Explorer. Fields that appear in black are editable. When you select an editable field, an edit button is displayed next to the selected field value.



User interface elements are described below:

UI Element	Description
	Enables you to edit the value for the selected field.
<b>Graph fields</b>	<ul style="list-style-type: none"><li><b>Filter</b>. Shows configured filter.</li><li><b>Granularity</b>. Shows configured granularity.</li><li><b>Group By</b>. Shows the filter for selected group.</li><li><b>Measurement Breakdown</b>. Shows the measurements of the graph.</li><li><b>Title</b>. Shows the name of the graph in the graph display window.</li></ul>

UI Element	Description
<b>Summary Report fields</b>	<ul style="list-style-type: none"><li><b>Description.</b> A short summary of what is included in the summary report.</li><li><b>Filter.</b> Shows configured filter for the summary report.</li><li><b>Percentile.</b> The Summary Report contains a percentile column showing the response time of 90% of transactions (90% of transactions that fall within this amount of time). To change the value of the default 90 percentile, enter a new figure in the <b>Transaction Percentile</b> box.</li><li><b>Title.</b> The name of the summary report.</li></ul>
<b>Transaction Analysis Report fields</b>	When clicking the edit button for some of the fields, the Analyze Transaction Settings dialog box opens, enabling you to edit some of the Analyze Transaction settings.

## Viewing Load Test Scenario Information

### ***Viewing Load Test Scenario Information***


In Analysis, you can view information about the load test scenario which you are analyzing. You can view the scenario run time settings and output messages that were generated by the Controller during the scenario.

You can view information about the Vuser groups and scripts that were run in each scenario, as well as the run time settings for each script in a scenario, in the Scenario Run Time Settings dialog box.

**Note:** The run time settings allow you to customize the way a Vuser script is executed. You configure the run time settings from the Controller or Virtual User Generator (VuGen) before running a scenario. For information on configuring the run time settings, refer to the *HP Virtual User Generator User Guide*.

Choose **File > View Scenario Run Time Settings**, or click **View Run Time Settings** on the toolbar.

The Scenario Run Time Settings dialog box opens, displaying the Vuser groups, scripts, and scheduling information for each scenario. For each script in a scenario, you can view the run time settings that were configured in the Controller or VuGen before scenario execution.




## How to Configure Controller Output Messages Settings

This task describes how to configure settings for output messages.

1. Choose **Tools > Options** and select the **Result Collection** tab.
2. In the **Copy Controller Output Messages to Analysis Session** area, choose one of the following options:
  - **Copy if data set is smaller than X MB.** Copies the Controller output data to the Analysis session if the data set is smaller than the amount you specify.
  - **Always Copy.** Always copies the Controller output data to the Analysis session.
  - **Never Copy.** Never copies the Controller output data to the Analysis session.
3. Apply your settings.
  - To apply these settings to the current session, click **Apply now to active session**.
  - To apply these settings after the current session is saved, click **OK**.

## Controller Output Messages Window

This window displays error, notification, warning, debug, and batch messages that are sent to the Controller by the Vusers and load generators during a scenario run.



To access	<b>Window &gt; Controller Output Messages</b>
Important information	<ul style="list-style-type: none"> <li>The Summary tab is displayed by default when you open this window.</li> <li>Analysis searches for the output data in the current Analysis session. If the data is not found, it searches in the scenario results folder. If Analysis cannot locate the results folder, no messages are displayed.</li> </ul>

User interface elements are described below:

UI Element	Description
<b>Summary Tab</b>	See " <a href="#">Summary Tab</a> " below
<b>Filtered Tab</b>	See " <a href="#">Filtered Tab</a> " on page 1430


## Summary Tab

This tab displays summary information about the messages sent during a scenario run.

To access	<b>Controller Output Messages</b> window > <b>Summary</b> tab
Important Information	You can drill down further on any information displayed in blue.
Parent topic	<a href="#">"Controller Output Messages Window" on the previous page</a>
See also	<a href="#">"Filtered Tab" on page 1430</a>

User interface elements are described below:

UI Element	Description
	Displays the full text of the selected output message in the Detailed Message Text area at the bottom of the Output window.
	<b>Remove all messages.</b> Clears all log information from the Output window.
	<b>Export the view.</b> Saves the output to a specified file.

UI Element	Description
 Freeze	<ul style="list-style-type: none"> <li><b>Freeze.</b> Stops updating the Output window with messages.</li> </ul>
 Resume	<ul style="list-style-type: none"> <li><b>Resume.</b> Resumes updating the Output window with messages. The newly updated log information is displayed in a red frame.</li> </ul>
<b>Detailed Message Text</b>	Displays the full text of the selected output message when you click the <b>Details</b> button.
<b>Generators</b>	Displays the number of load generators that generated messages with the specified message code.
<b>Help</b>	Displays an icon if there is a link to troubleshooting for the message.
<b>Message Code</b>	Displays the code assigned to all similar messages. The number in parentheses indicates the number of different codes displayed in the Output window.
<b>Sample Message Text</b>	Displays an example of the text of a message with the specified code.
<b>Scripts</b>	Displays the number of scripts whose execution generated messages with the specified code.
<b>Total Messages</b>	Displays the total number of sent messages with the specified code.
<b>Type</b>	<p>The type of message being displayed. The following icons indicate the various message types. For more information about each type, see <b>Type of Message</b> below:</p> <ul style="list-style-type: none"> <li> Batch</li> <li> Debug</li> <li> Errors</li> <li> Notifications</li> <li> Warnings</li> <li> Alerts</li> </ul>

UI Element	Description
Type of Message	<p>Filters the output messages to display only certain message types. Select one of the following filters:</p> <ul style="list-style-type: none"> <li>• <b>All messages.</b> Displays all message types.</li> <li>• <b>Batch.</b> Sent instead of message boxes appearing in the Controller, if you are using automation.</li> <li>• <b>Debug.</b> Sent only if the debugging feature is enabled in the Controller. (Expert mode: <b>Tools &gt; Options &gt; Debug Information</b>). For more information, see "Options &gt; Debug Information Tab" on page 242.</li> <li>• <b>Errors.</b> Usually indicate that the script failed.</li> <li>• <b>Notifications.</b> Provides run-time information, such as message sent using <code>lr_output_message</code>.</li> <li>• <b>Warnings.</b> Indicates that the Vuser encountered a problem, but the scenario continued to run.</li> <li>• <b>Alerts.</b> Indicates a warning.</li> </ul>
Vusers	Displays the number of Vusers that generated messages with the specified code.

## Filtered Tab

This tab displays a drilled down view by message, Vuser, script, or load generator. For example, if you drill down on the Vuser column, the Filtered tab displays all the messages with the code you selected, grouped by the Vusers that sent the messages.

To access	Controller Output Messages window > <b>Summary</b> tab. Click the blue link on the column that you wish to view more information about.
Important information	The tab appears when you click on a blue link in the Summary tab.
See also	<a href="#">"Summary Tab" on page 1428</a>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
	<b>Previous/Next View.</b> Enables you to move between the various drill down levels.
 Details	Displays the full text of the selected output message in the Detailed Message Text area at the bottom of the Output window.

UI Element	Description
	<b>Export the view.</b> Saves the output to a specified file.
 Refresh	Refreshes the Filtered tab with new log information that arrived in the Output window updated in the Summary tab.
<Message icon>	Displays an icon indicating the type of message by which the current Output view is filtered.
<b>Active Filter</b>	Displays the category or categories by which the current Output view is filtered.
<b>Viewed By</b>	Displays the name of the column on which you selected to drill down. The following icons indicate the various message types: <ul style="list-style-type: none"> <li>•  Batch</li> <li>•  Debug</li> <li>•  Errors</li> <li>•  Notifications</li> <li>•  Warnings</li> <li>•  Alerts</li> </ul>
<b>Detailed Message Text</b>	Displays the full text of the selected output message when the <b>Details</b> button is selected.
<b>Message</b>	Displays all instances of the sample message text.
<b>Script</b>	The script on which the message was generated. If you click the blue link, VuGen opens displaying the script.
<b>Action</b>	The action in the script where the message was generated. If you click the blue link, VuGen opens the script to the relevant action.
<b>Line #</b>	The line in the script where the message was generated. If you click the blue link, VuGen opens the script and highlights the relevant line.
<b># Lines</b>	The total number of lines in the script where the Vuser failed.
<b>Time</b>	The time the message was generated.
<b>Iteration</b>	The iteration during which the message was generated.

UI Element	Description
<b>Vuser</b>	The Vuser that generated the message.
<b>Generator</b>	The load generator on which the message was generated. If you click the blue link, the Load Generator dialog box opens.
<b># Messages</b>	The number of messages generated by a specific Vuser.

## ***Scenario Run Time Settings Dialog Box***

This dialog box enables you to view information about executed load test scenarios, as well as the run time settings for each script in a scenario.

<b>To access</b>	Toolbar > 
<b>See also</b>	<a href="#">"Viewing Load Test Scenario Information" on page 1426</a>

User interface elements are described below

UI Element	Description
<b>Result Name</b>	The name of the result file.
<b>Scenario Scripts</b>	Displays the result set for each executed scenario, as well as the Vuser groups and scripts that were run in the scenario.
<b>Group Name</b>	Displays the name of the group to which the selected script belongs.
<b>Full Path</b>	Displays the script's full directory path.
<b>Script Name</b>	Displays the name of the selected script.
<b>Scenario Schedule</b>	Displays goal-oriented or manual scenario scheduling information for the selected scenario.
<b>View Script</b>	Opens the Virtual User Generator, so that you can edit the script. For more information on editing scripts, refer to the <i>HP Virtual User Generator User Guide</i> .

## **Cross Result and Merged Graphs**

### ***Cross Result and Merged Graphs Overview***

Comparing results is essential for determining bottlenecks and problems. You use Cross Result graphs to compare the results of multiple load test scenario runs. You create Merged graphs to compare results from different graphs within the same scenario run.

## Cross Result Graphs Overview

Cross Result graphs are useful for:

- Benchmarking hardware
- Testing software versions
- Determining system capacity


If you want to benchmark two hardware configurations, you run the same load test scenario with both configurations and compare the transaction response times using a single Cross Result graph.

Suppose that your vendor claims that a new software version is optimized to run quicker than a previous version. You can verify this claim by running the same scenario on both versions of the software, and comparing the scenario results.

You can also use Cross Result graphs to determine your system's capacity. You run scenarios using different numbers of Vusers running the same script. By analyzing Cross Result graphs, you can determine the number of users that cause unacceptable response times.

In the following example, two scenario runs are compared by crossing their results, **res12**, and **res15**. The same script was executed twice—first with 100 Vusers and then with 50 Vusers.

In the first run, the average transaction time was approximately 59 seconds. In the second run, the average time was 4.7 seconds. It is apparent that the system works much slower with a greater load.



The Cross Result graphs have an additional filter and group by category: **Result Name**. The above graph is filtered to the **OrderRide** transaction for results **res12**, and **res15**, grouped by **Result Name**.


## Merging Types Overview

Analysis provides three types of merging:

### Overlay


Superimpose the contents of two graphs that share a common x-axis. The left y-axis on the merged graph shows the current graph's values. The right y-axis shows the values of the graph that was merged. There is no limit to the number of graphs that you can overlay. When you overlay two graphs, the y-axis for each graph is displayed separately to the right and left of the graph. When you overlay more than two graphs, Analysis displays a single y-axis, scaling the different measurements accordingly.

In the following example, the Throughput and Hits per Second graph are overlaid with one another.



### Tile


View contents of two graphs that share a common x-axis in a tiled layout, one above the other. In the following example the Throughput and Hits per Second graph are tiled one above the other.



## Correlate

Plot the y-axis of two graphs against each other. The active graph's y-axis becomes the x-axis of the merged graph. The y-axis of the graph that was merged, becomes the merged graph's y-axis.

In the following example, the Throughput and Hits per Second graph are correlated with one another. The x-axis displays the bytes per second (the Throughput measurement) and the y-axis shows the average hits per second.



## How to Generate Cross Results Graphs

This task describes how to create a Cross Result graph for two or more result sets. The Cross Result dialog box enables you to compare the results of multiple load test scenario runs.

1. Choose **File > Cross With Result**. The Cross Results dialog box opens.
2. Click **Add** to add an additional result set to the **Result List**. The Select Result Files for Cross Results dialog box opens.
3. Locate a results folder and select its result file (.Irr). Click **OK**. The scenario is added to the Result List.
4. Repeat steps 2 and 3 until all the results you want to compare are in the Result List.
5. When you generate a Cross Result graph, by default it is saved as a new Analysis session. To save it in an existing session, clear the **Create New Analysis Session for Cross Result** box.
6. Click **OK**. Analysis processes the result data and asks for a confirmation to open the default graphs.

**Note:** When generating a Cross Results Session, verify that the transaction names do not contain a <\_> or <@> symbol. This will cause errors to occur when attempting to open the Cross Results graphs.

After you generate a Cross Result graph, you can filter it to display specific scenarios and transactions. You can also manipulate the graph by changing the granularity, zoom, and scale.

You can view a summary report for the Cross Result graph.

## How to Generate Merged Graphs

This task describes how to merge the results of two graphs from the same load test scenario into a single graph. The merging allows you to compare several different measurements at once. For example, you can make a merged graph to display the network delay and number of running Vusers, as a function of the elapsed time.

You can merge all graphs with a common x-axis.

1. Select a graph in the Session Explorer or select its tab to make it active.
2. Choose **View > Merge Graphs** or click **Merge Graphs**. The Merge Graphs dialog box opens and displays the name of the active graph.
3. Select a graph with which you want to merge your active graph. Only the graphs with a

common x-axis to the active graph are available.

4. Select the merge type and a title for the merged graph. By default, Analysis combines the titles of the two graphs being merged. For more information, see "[Merge Graphs Dialog Box](#)" below.
5. Click **OK**.
6. Filter the graph just as you would filter any ordinary graph.

## Merge Graphs Dialog Box

This dialog box enables you to merge two graphs into a single graph.

To access	<b>View &gt; Merge Graphs</b>
<b>Important information</b>	In order to merge graphs, the graphs' x-axes must be the same measurement. For example, you can merge Web Throughput and Hits per Second graphs, because their x-axes are Scenario Elapsed Time.
<b>See also</b>	<a href="#">"Merging Types Overview" on page 1434</a>

User interface elements are described below:

UI Element	Description
<b>Select Graph to merge with</b>	The drop-down list shows all of the open graphs that share a common x-axis measurement with the current graph. Select one of the graphs in the list.
<b>Select type of merge</b>	<ul style="list-style-type: none"><li>• <b>Overlay</b>. View contents of two graphs that share a common x-axis. The left y-axis on the merged graph shows the current graph's values. The right y-axis shows the values of the graph that was merged with the current graph.</li><li>• <b>Tile</b>. View contents of two graphs that share a common x-axis in a tiled layout, one above the other.</li><li>• <b>Correlate</b>. Plot the y-axes of two graphs against each other. The active graph's y-axis becomes the x-axis of the merged graph. The y-axis of the graph that was merged, becomes the merged graph's y-axis.</li></ul>
<b>Title of Merged Graph</b>	Enter a title for the merged graph. This title will appear in the Session Explorer ( <a href="#">Windows &gt; Session Explorer</a> ).

## Defining Service Level Agreements

## Service Level Agreements Overview

**Service level agreements (SLAs)** are specific goals that you define for your load test scenario. After a scenario run, HP LoadRunner Analysis compares these goals against performance related data that was gathered and stored during the course of the run, and determines whether the SLA passed or failed.

Depending on the measurements that you are evaluating for your goal, LoadRunner determines the SLA status in one of the following ways:

SLA Type	Description
<b>SLA status determined at time intervals over a timeline</b>	<p>Analysis displays SLA statuses at set time intervals over a timeline within the run. At each time interval in the timeline—for example, every 10 seconds—Analysis checks to see if the measurement's performance deviated from the threshold defined in the SLA.</p> <p>Measurements that can be evaluated in this way:</p> <ul style="list-style-type: none"><li>• <b>Transaction Response Time (Average) per time interval</b></li><li>• <b>Errors per Second per time interval</b></li></ul>
<b>SLA status determined over the whole run</b>	<p>Analysis displays a single SLA status for the whole scenario run.</p> <p>Measurements that can be evaluated in this way:</p> <ul style="list-style-type: none"><li>• <b>Transaction Response Time (Percentile) per run</b></li><li>• <b>Total Hits per run</b></li><li>• <b>Average Hits (hits/second) per run</b></li><li>• <b>Total Throughput (bytes) per run</b></li><li>• <b>Average Throughput (bytes/second) per run</b></li></ul>

You can define and edit SLAs in the Controller or in Analysis.

## Tracking Period

When you define service level agreements (SLAs) an SLA for measurements that are evaluated over a timeline, Analysis determines SLA statuses at specified time intervals within that timeline. The frequency of the time intervals is called the **tracking period**.

An internally-calculated tracking period is defined by default. You can change the tracking period by entering a value in the Advanced Options dialog box which Analysis plugs into a built-in algorithm to calculate the tracking period. For details, see "[Advanced Options Dialog Box \(Service Level Agreement Pane\)](#)" on page 1443.

## How to Define Service Level Agreements



This task describes how to define service level agreements (SLAs).

You can define service level agreements (SLAs) which measure scenario goals over time intervals, or over a whole scenario run. For details, see "[Service Level Agreements Overview](#)" on the previous page.

**Tip:** For a use-case scenario related to this task, see "[How to Define Service Level Agreements - Use-Case Scenario](#)" on the next page.

### 1. Prerequisites

If you are defining an SLA for Average Transaction Response Time, your scenario must include a script that contains at least one transaction.

### 2. Run through the SLA wizard

In the Service Level Agreement pane, click **New** to open the Service Level Agreement wizard. For user interface details, see "[Service Level Agreement Wizard](#)" on page 1445.

- a. Select a measurement for the SLA.
- b. If you are defining an SLA for Average Transaction Response Time or Transaction Response Time (Percentile), select the transactions to include in your goal.
- c. (Optional) When evaluating SLA statuses over a timeline, select load criteria to take into account and define appropriate load value ranges for the load criteria. For an example, see "[How to Define Service Level Agreements - Use-Case Scenario](#)" on the next page.
- d. Set thresholds for the measurements.
  - o If the **Average Transaction Response Time** or **Errors per Second** exceed the defined thresholds, Analysis will produce a **Failed** SLA status.
  - o If **Transaction Response Time(Percentile)**, **Total Hits per run**, **Average Hits (hits/second)** per run, **Total Throughput (bytes)** per run, or **Average Throughput (bytes/second)** per run are lower than the defined threshold, Analysis will produce a **Failed** SLA status.

### 3. Define a tracking period - optional

For measurements whose SLA statuses are determined over time intervals, you need to define

the frequency of the time intervals, that is, the **tracking period**. For details, see ["Tracking Period" on page 1438](#).

For user interface details, see ["Advanced Options Dialog Box \(Service Level Agreement Pane\)" on page 1443](#).

#### 4. Results

When analyzing your scenario run, HP LoadRunner Analysis compares the data collected from the scenario run against the SLA settings, and determines SLA statuses which are included in the default Summary Report.

## **How to Define Service Level Agreements - Use-Case Scenario**

This use-case scenario describes how to define a service level agreement (SLA) for Average Transaction Response Time.

#### 1. Background

The administrator of HP Web Tours would like to know when the average transaction response time for booking a flight and searching for a flight exceeds a certain value. Assume that your scenario includes a script that includes the following transactions: **book\_flight** and **search\_flight**.

#### 2. Start the SLA wizard


In the Service Level Agreement pane, click **New** to open the Service Level Agreement wizard.

#### 3. Select the measurement for the SLA

On the Select a Measurement page, under **Select a Measurement for Your Goal**, in the **Transaction Response Time** box, select **Average**.

#### 4. Select the transactions to evaluate in your goal

On the Select a Transaction page, select the transactions to be evaluated: **book\_flight** and **search\_flight**.



## 5. Select a load criterion and define appropriate ranges of load - optional

On the Select Load Criteria page, select the load criterion to take into account when evaluating the average transaction response time.


In this case, to see the effect that various quantities of Vusers running on the system has on the average transaction response time of each transaction, in the **Load Criteria** box, select **Running Vusers**.

Then set the value ranges for the running Vusers:

Consider less than 20 Vusers to be a light load, 20 – 50 Vusers an average load, and 50 Vusers or more a heavy load. Enter these values in the Load Values boxes.

### Note:

- You can set up to three in-between ranges.
- Valid load value ranges are consecutive—there are no gaps in the range—and span all values from zero to infinity.



## 6. Set thresholds

On the Set Threshold Values page, you define the acceptable average transaction response times for the transactions, taking into account the defined load criteria.

In this case, define the same threshold values for both transactions as follows: for a light load, a reasonable average response time can be up to 5 seconds, for an average load, up to 10 seconds, and for a heavy load, up to 15 seconds.

Running Vusers			
Transaction Name	<20	≥20 and <50	≥50
book_flight	5	10	15
search_flight	5	10	15

**Tip:** To define the same thresholds for all the transactions, you can type the values in the table nearer the bottom of the Set Threshold Values page, and click **Apply to all transactions**.

## 7. Define a tracking period - optional

When SLA statuses for a measurement are determined at time intervals over a timeline, the frequency of the time intervals is determined by the **tracking period**.

This step is optional because an internally-calculated tracking period of at least 5 seconds is defined by default. You can change the tracking period in the Advanced Options dialog box:

- a. In the Service Level Agreement pane, click the **Advanced** button.
- b. Select **Tracking period of at least X seconds**, and select a tracking period. The time intervals are calculated by Analysis according to a built-in algorithm and as a function of the value you enter here.

### Example:

If you select a tracking period of 10, and the aggregation granularity for the scenario (defined in Analysis) is 6, then the tracking period is set to the nearest multiple of 6 that is greater than or equal to 10, that is, Tracking Period = 12.

For details, see "["Tracking Period" on page 1438](#).

For user interface details, see "["Advanced Options Dialog Box \(Service Level Agreement Pane\)" on the next page](#).

## 8. Results

When analyzing your scenario run, Analysis applies your SLA settings to the default Summary Report and the report is updated to include all the relevant SLA information.


For example, it displays the worst performing transactions in terms of defined SLAs, how specific transactions performed over set time intervals, and overall SLA statuses.

## Service Level Agreement Pane

This pane lists all the service level agreements (SLAs) defined for the scenario.

To access	Tools menu > Configure SLA Rules > Service Level Agreement pane
<b>Relevant Tasks</b>	<ul style="list-style-type: none"><li>"How to Design a Goal-Oriented Scenario" on page 1043</li><li>"How to Design a Manual Scenario" on page 1045</li><li>"How to Define Service Level Agreements" on page 1439</li><li>"How to Define Service Level Agreements - Use-Case Scenario" on page 1440</li></ul>
<b>See also</b>	"Service Level Agreements Overview" on page 1438

User interface elements are described below:

UI Element	Description
 New	Starts the Service Level Agreement wizard where you can define new goals for the load test scenario.
 Details	Opens the Goal Details dialog box which displays a summary of the details of the selected SLA.
 Edit	Opens the Service Level Agreement wizard where you can modify the goals defined in the SLA.
 Delete	Deletes the selected SLA.
 Advanced	Opens the Advanced Options dialog box where you can adjust the tracking period for measurements that are evaluated per time interval over a timeline.  For more information, see "Tracking Period" on page 1438.  For user interface details, see "Advanced Options Dialog Box (Service Level Agreement Pane)" below.
<b>Service Level Agreement list</b>	Lists the SLAs defined for the scenario.

## Advanced Options Dialog Box (Service Level Agreement Pane)

This dialog box enables you to define a tracking period for load test scenario.

To access	Tools menu > <b>Configure SLA Rules</b> > <b>Service Level Agreement</b> pane >  Advanced
Important information	The tracking period is calculated by Analysis according to a built-in algorithm and as a function of the value entered here.
Relevant tasks	<ul style="list-style-type: none"> <li>"<a href="#">How to Define Service Level Agreements</a>" on page 1439</li> <li>"<a href="#">How to Define Service Level Agreements - Use-Case Scenario</a>" on page 1440</li> </ul>
See also	<a href="#">"Service Level Agreements Overview"</a> on page 1438

User interface elements are described below:

UI Element	Description
<b>Internally calculated tracking period</b>	<p>Analysis sets the tracking period to the minimum value possible, taking into account the aggregation granularity defined for the scenario. This value is at least 5 seconds. It uses the following formula:</p> $\text{Tracking Period} = \text{Max (5 seconds, aggregation granularity)}$
<b>Tracking period of at least X seconds</b>	<p>Determines the minimum amount of time for the tracking period. This value can never be less than 5 seconds.</p> <p>Analysis sets the tracking period to the nearest multiple of the scenario's aggregation granularity that is greater than or equal to the value (X) that you selected.</p> <p>For this option, Analysis uses the following formula:</p> $\text{Tracking Period} = \text{Max(5 seconds, } m(\text{Aggregation Granularity}))$ <p>where <b>m</b> is a multiple of the scenario's aggregation granularity such that <b>m (Aggregation Granularity)</b> is greater than or equal to <b>X</b>.</p> <p><b>Example:</b> If you select a tracking period of X=10, and the aggregation granularity for the scenario is 6, then the tracking period is set to the nearest multiple of 6 that is greater than or equal to 10, that is, Tracking Period = 12.</p>

## Goal Details Dialog Box (Service Level Agreement Pane)

This dialog box displays the thresholds that were set for the selected SLA.

To access	Tools menu > <b>Configure SLA Rules</b> > <b>Service Level Agreement</b> pane >  Details
Important information	If you defined load criteria as part of your SLA, the threshold values are displayed per the defined load value ranges.

**See also**

"Service Level Agreements Overview" on page 1438

## Service Level Agreement Wizard

This wizard enables you to define goals or **service level agreements** (SLAs) for your load test scenario.

<b>To access</b>	Tools menu > Configure SLA Rules > Service Level Agreement pane > 
<b>Important information</b>	There are two modes for the Service Level Agreement wizard. The pages included in the wizard depend on the measurement that is selected. See the wizard maps below.
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>"How to Define Service Level Agreements" on page 1439</li><li>"How to Define Service Level Agreements - Use-Case Scenario" on page 1440</li></ul>
<b>Wizard map - Goal measured per time interval</b>	The <b>Service Level Agreement Wizard</b> contains: <b>Welcome</b> > "Select a Measurement Page" below > ("Select Transactions Page" on the next page) > "Set Load Criteria Page" on page 1447 > "Set Threshold Values Page (Goal Per Time Interval)" on page 1449
<b>Wizard map - Goal measured over whole scenario run</b>	The <b>Service Level Agreement Wizard</b> contains: <b>Welcome</b> > "Select a Measurement Page" below > ("Select Transactions Page" on the next page) > "Set Threshold Values Page (Goal Per Whole Run)" on page 1450
<b>See also</b>	"Service Level Agreements Overview" on page 1438

## Select a Measurement Page

This wizard page enables you to select a measurement for your goal.

<b>Important information</b>	<ul style="list-style-type: none"><li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" above.</li><li>There are two modes for the Service Level Agreement wizard. The wizard pages that follow depend on the measurement that you select on this page. See the wizard maps below.</li></ul>
<b>Wizard map - Goal measured per time interval</b>	The " <a href="#">Service Level Agreement Wizard</a> " above contains: <b>Welcome</b> > <a href="#">Select a Measurement Page</a> > ("Select Transactions Page" on the next page) > "Set Load Criteria Page" on page 1447 > "Set Threshold Values Page (Goal Per Time Interval)" on page 1449

<b>Wizard map - Goal measured over whole scenario run</b>	The "Service Level Agreement Wizard" on the previous page contains:  <b>Welcome &gt; Select a Measurement Page &gt; ("Select Transactions Page" below) &gt; "Set Threshold Values Page (Goal Per Whole Run)" on page 1450</b>
<b>See also</b>	"Service Level Agreements Overview" on page 1438

User interface elements are described below:

UI Element	Description
<b>SLA status determined over the whole run</b>	Evaluates a single SLA status for the whole scenario run. Select one of the following measurements: <ul style="list-style-type: none"><li>• <b>Transaction Response Time (Percentile)</b></li><li>• <b>Total Hits per run</b></li><li>• <b>Average Hits (hits/second) per run</b></li><li>• <b>Total Throughput (bytes) per run</b></li><li>• <b>Average Throughput (bytes/second) per run</b></li></ul>
<b>SLA status determined per time intervals over a timeline</b>	Evaluates SLA statuses at set time intervals within the run. Select one of the following measurements: <ul style="list-style-type: none"><li>• <b>Average Transaction Response Time</b></li><li>• <b>Errors per Second</b></li></ul> <p>The time intervals at which the SLA statuses are evaluated are known as the <b>tracking period</b>. For details, see "<a href="#">"Tracking Period" on page 1438</a>.</p>

## Select Transactions Page

This wizard page enables you to select transactions to evaluate as part of your goal.

<b>Important information</b>	<ul style="list-style-type: none"> <li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1445.</li> <li>This page is displayed when creating an SLA for Transaction Response Time by Average or by Percentile.</li> <li>In order to define an SLA for Transaction Response Time by Average or by Percentile, at least one of the Vuser scripts participating in the scenario must include a transaction.</li> <li>You can select multiple transactions using the CTRL key.</li> </ul>
<b>Wizard map - Goal measured per time interval</b>	<p>The "<a href="#">Service Level Agreement Wizard</a>" on page 1445 contains:</p> <p><b>Welcome</b> &gt; "<a href="#">Select a Measurement Page</a>" on page 1445 &gt; (<b>Select Transactions Page</b>) &gt; "<a href="#">Set Load Criteria Page</a>" below &gt; "<a href="#">Set Threshold Values Page (Goal Per Time Interval)</a>" on page 1449</p>
<b>See also</b>	<a href="#">"Service Level Agreements Overview"</a> on page 1438

User interface elements are described below:

UI Element	Description
<b>Available Transactions</b>	<p>Lists the transactions in the Vuser scripts participating in the scenario.</p> <p>To move a script to the <b>Selected Transaction</b> list, select it and click <b>Add</b>.</p>
<b>Selected Transactions</b>	<p>Lists the transactions in the Vuser scripts participating in the scenario that have been selected for the SLA.</p> <p>To remove a script from this list, select it and click <b>Remove</b>.</p>

## Set Load Criteria Page

This wizard page enables you to select load criteria to take into account when testing your goal.

<b>Important information</b>	<ul style="list-style-type: none"> <li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1445.</li> <li>This page is displayed only when defining an SLA that determines SLA statuses per time interval over a timeline.</li> <li>In the next wizard step (Set Threshold Values page), you will set different thresholds per each of the load ranges that you select here.</li> </ul>
<b>Wizard map - Goal measured per time interval</b>	<p>The "<a href="#">Service Level Agreement Wizard</a>" on page 1445 contains:</p> <p><b>Welcome</b> &gt; "<a href="#">Select a Measurement Page</a>" on page 1445 &gt; ("Select Transactions Page" on the previous page) &gt; <b>Set Load Criteria Page</b> &gt; "<a href="#">Set Threshold Values Page (Goal Per Time Interval)</a>" on page 1449</p>

, continued

See also	<a href="#">"Service Level Agreements Overview" on page 1438</a>
----------	------------------------------------------------------------------

User interface elements are described below:

UI Element	Description
<b>Load Criteria</b>	<p>The relevant load criteria that you want to use</p> <p><b>Example:</b> If you want to see the impact of running Vusers on the measurement, select <b>Running Vusers</b>.</p> <p>To define an SLA without load criteria, select <b>None</b>.</p>
<b>Load Values</b>	<p>Valid load value ranges are consecutive—there are no gaps in the range—and span all values from zero to infinity.</p> <ul style="list-style-type: none"><li>• <b>Less than.</b> Enter the upper value for the lower range of values for the load criteria.</li></ul> <p>The lower range is between 0 and the value you entered. It does not include the upper value.</p> <p><b>Example:</b> If you enter 5, the lower range of values for the load criteria is between 0 and 5, but does not include 5.</p> <ul style="list-style-type: none"><li>• <b>Between.</b> The in-between range of values for the load criteria. Enter lower and upper values for this range. The lower range is included in this range; it does not include the upper value.</li></ul> <p><b>Example:</b> If you enter 5 and 10, the in-between range of values for the load criteria is from 5 and up to, but not including, 10.</p> <p><b>Note:</b> You can set up to three in-between ranges.</p> <ul style="list-style-type: none"><li>• <b>Greater than.</b> Enter the lower value for the upper range of values for the load criteria.</li></ul> <p>The upper range includes values from the value you entered and on.</p> <p><b>Example:</b> If you enter 10, the upper range of values for the load criteria is from 10 and on.</p>
<b>Selected Measurement</b>	The measurement selected for the goal.

## **Set Percentile Threshold Values Page**

This wizard page enables you to select load criteria to take into account when testing your goal.

<b>Important information</b>	<ul style="list-style-type: none"><li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1445.</li><li>The Percentile SLA enables you to measure whether the percentage of transaction samples meets the defined threshold criteria.</li><li>You can enter a threshold value to 3 decimal places.</li></ul>
<b>Wizard map - Goal measured over whole scenario run</b>	The " <a href="#">Service Level Agreement Wizard</a> " on page 1445 contains: <b>Welcome</b> > " <a href="#">Select a Measurement Page</a> " on page 1445 > (" <a href="#">Select Transactions Page</a> " on page 1446) > <b>Set Percentile Threshold Values Page</b>
<b>See also</b>	<a href="#">"Service Level Agreements Overview" on page 1438</a>

User interface elements are described below:

UI Element	Description
<b>Selected Measurement</b>	The measurement selected for the goal.
<b>Percentile</b>	Percentage of transactions to measure against the configured threshold.
<b>Provide threshold value for all transactions</b>	To apply one set of threshold values to all transactions selected for the goal, enter the threshold value and click <b>Apply to all</b> . These values are applied to all the transactions in the Thresholds table at the bottom of the page.
<b>Transaction name</b>	The transaction from the scenario run.
<b>Threshold</b>	The threshold value for the selected transaction.

## **Set Threshold Values Page (Goal Per Time Interval)**

This wizard page enables you to set thresholds for the measurements you are evaluating in your goal.

<b>Important information</b>	<ul style="list-style-type: none"><li>General information about this wizard is available here: "<a href="#">Service Level Agreement Wizard</a>" on page 1445.</li><li>If you defined load criteria in the "<a href="#">Set Load Criteria Page</a>" on page 1447, you must set thresholds per each of the defined load ranges. If you did not define load criteria, you set one threshold value. For Average Transaction response time, you set threshold values for each transaction.</li><li>You can enter a threshold value to 3 decimal places.</li></ul>
------------------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

<b>Wizard map - Goal measured per time interval</b>	The "Service Level Agreement Wizard" on page 1445 contains: <b>Welcome &gt; "Select a Measurement Page" on page 1445 &gt; ("Select Transactions Page" on page 1446) &gt; "Set Load Criteria Page" on page 1447 &gt; Set Threshold Values Page (Goal Per Time Interval)</b>
<b>See also</b>	"Service Level Agreements Overview" on page 1438

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Thresholds table>	The thresholds for your goal. If you defined load criteria, enter thresholds for each range of values.  <b>Note:</b> If the maximum threshold value is exceeded during a particular time interval during the run, Analysis displays an SLA status of <b>Failed</b> for that time interval.
<b>Apply to all</b> (Average Transaction Response Time goal only)	To apply one set of threshold values to all transactions selected for the goal, enter the threshold values in this table and click <b>Apply to all transactions</b> . These values are applied to all the transactions in the Thresholds table at the top of the page.  <b>Note:</b> Threshold values for selected transactions do not have to be the same. You can assign different values for each transaction.
<b>Selected Measurement</b>	The measurement selected for the goal.

## **Set Threshold Values Page (Goal Per Whole Run)**

This wizard page enables you to set minimum thresholds for the measurements you are evaluating in your goal.

<b>Important information</b>	General information about this wizard is available here: <a href="#">"Service Level Agreement Wizard" on page 1445</a> .
<b>Wizard map - Goal measured over whole scenario run</b>	The "Service Level Agreement Wizard" on page 1445 contains:  <b>Welcome &gt; "Select a Measurement Page" on page 1445 &gt; Set Threshold Values Page (Goal Per Whole Run)</b>
<b>See also</b>	"Service Level Agreements Overview" on page 1438

User interface elements are described below:

UI Element	Description
<b>Selected measurement</b>	The measurement selected for the goal.
<b>Threshold</b>	The minimum threshold value for the selected measurement. <b>Note:</b> If the value of the measurement is lower than this threshold during the run, Analysis displays an SLA status of <b>Failed</b> for the entire run.

## Working with Application Lifecycle Management

### ***Managing Results Using ALM - Overview***

Analysis works together with HP Application Lifecycle Management (ALM). ALM provides an efficient method for storing and retrieving scenario and analysis results. You can store results in an ALM project and organize them into unique groups.

In order for the Analysis to access an ALM project, you must connect it to the Web server on which ALM is installed. You can connect to either a local or remote Web server.

When working against an ALM server with Performance Center, the ALM integration has several additional capabilities, such as the ability to save the Analysis session to a new location, and upload a report from the file system to ALM. For details, see "[How to Work with Results in ALM - With Performance Center](#)" on page 1453.

For more information on working with ALM, see the *Application Lifecycle Management User Guide*.

### ***How to Connect to ALM***

To store and retrieve results from ALM, you need to connect to an ALM project. You can connect or disconnect from an ALM project at any time during the testing process.

You can connect to one version of HP ALM from Analysis and a different version from your browser. For more information, see the **Important Information** section in "[HP ALM Connection Dialog Box](#)" on page 1456.

#### **Connect to ALM**

1. Select **Tools > HP ALM Connection**. The HP ALM Connection dialog box opens.
2. Enter the required information in the HP ALM Connection dialog box, as described in "[HP ALM Connection Dialog Box](#)" on page 1456.
3. To disconnect from ALM, click **Disconnect**.

## **How to Work with Results in ALM - Without Performance Center**

The following steps describe the workflow for working with results saved in an ALM project, whose server does not have a Performance Center installation.

When working against an ALM server with HP Performance Center, there are several differences. For more information, see "[How to Work with Results in ALM - With Performance Center](#)" on the [next page](#).

### **1. Connect to ALM**

Open a connection to the ALM server and project that contains the LoadRunner result or Analysis session files. For task details, see "[How to Connect to ALM](#)" on the previous page.

### **2. Open an existing Analysis session file - optional**

- a. Select **File > Open**.
- b. In the left pane select a script.
- c. In the right pane, select the results for which the Analysis session file was created.
- d. Click **OK**.

### **3. Create a new Analysis session file from the raw data - optional**

This procedure describes how to create a new Analysis session file on the ALM server, from the raw results file. If an Analysis session file already exists for the raw data, you can choose to overwrite the existing file.

- a. Select **File > New**.
- b. In the left pane select a script.
- c. In the right pane, select the results you want to analyze.
- d. Click **OK**.

### **4. Save the LoadRunner results file**

When you are finished analyzing your results and creating reports or graphs, save the changes. Select **File > Save**. The Analysis session file is in the ALM project.


**Note:** When working with ALM without Performance Center, **Save As** is not supported—you cannot save the Analysis session file to another location.

## How to Work with Results in ALM - With Performance Center

ALM servers with Performance Center, allow you to perform the following operations:

### Open an existing Analysis Session file


1. Select **Tools > HP ALM Connection** and make sure your connection to ALM is open.
2. Select **File > Open**.
3. Drill down to the Run level within the Test Plan module, and select an individual run.
4. Select a zip file containing the Analysis session file.



5. Click **Open**.

### Open raw data and create a new Analysis session


1. Select **Tools > HP ALM Connection** and make sure your connection to ALM is open.
2. To create a new Analysis session file from the raw data, select **File > New**.
3. Drill down to the Run level within the Test Plan module, and select an individual run.
4. Select a zip file containing the run's raw data.



5. Click **Open**.

### Save the changes to the Analysis session file

1. Complete your changes to the Analysis results.
2. Select **Tools > HP ALM Connection** and make sure your connection to ALM is open.
3. Select **File > Save**.
4. To save an Analysis session that was opened from the file system, click the **Test Lab** module button.
5. Drill down to the Run level within the Test Plan module, and specify a name for the zip file.




6. Provide a comment about the Analysis session (optional).

7. Click **Save**.

### Save the Analysis session file to a new ALM location

1. Select **Tools > HP ALM Connection** and make sure your connection to ALM is open.
2. Open an Analysis session file from the file system, or from ALM as described above.
3. Select **File > Save as**.
4. Drill down to the Run level within the Test Plan module, and select an individual run.
5. Specify a name for the Analysis session zip file. The name *Results* is reserved.



6. Provide a comment about the Analysis session (optional).
7. Click **Save**.

## How to Upload a Report to ALM

The following steps describe how to upload a report from the file system to an ALM's Test Lab module. This capability is only available for ALM installation with Performance Center.


When working against an ALM server with HP Performance Center, there are several differences. For more information, see "[How to Work with Results in ALM - With Performance Center](#)" on page [1453](#).

### 1. Connect to ALM

Open a connection to the ALM server and project that contains the LoadRunner result or Analysis session files. For task details, see "[How to Connect to ALM](#)" on page [1451](#).

## 2. Open the Upload dialog box

Select Tools > Upload Report to Test Lab.



## 3. Select a report

Click **Browse** in the **Step 1** section. The **Select the Report file** dialog box opens. Select an HTML or XML file from the file system. Click **Open**.

## 4. Select a location on ALM


Click **Browse** in the **Step 2** section. The **Select Location for the Report** dialog box opens. Navigate to a Run level in the Test Lab module. Specify a name for the report and include any relevant comments. Click **OK**.

## 5. Begin the upload

Click **Upload**. The upload begins.

## **HP ALM Connection Dialog Box**

This dialog box enables you to connect to an ALM project.




To access	Tools > HP ALM Connection
<b>Important information</b>	<p>You can connect to one version of HP ALM from LoadRunner and a different version of HP ALM from your browser.</p> <p>You can only connect to different versions of HP ALM if one of the versions is HP ALM 11.00 or higher.</p> <p><b>Note:</b> Before you connect to ALM through the LoadRunner interface, it is recommended that you first connect to the HP ALM server through your browser. This automatically downloads the ALM client files to your computer.</p>
<b>Relevant tasks</b>	<a href="#">"How to Connect to ALM" on page 1451</a>

User interface elements are described below:

UI Element	Description
<b>Step 1: Connect to Server</b>	<ul style="list-style-type: none"> <li><b>Server URL.</b> The URL of the server on which ALM is installed. The URL must be in the following form <b>http://&lt;server_name:port&gt;/qcbin</b>.</li> <li><b>Reconnect to server on startup.</b> Automatically reconnect to the server every time you start LoadRunner.</li> <li>•  /  . Connects to the server specified in the <b>Server URL</b> box. Only one button is visible at a time, depending on your connection status.</li> </ul>
<b>Step 2: Authenticate User Information</b>	<ul style="list-style-type: none"> <li><b>User Name.</b> Your ALM project user name.</li> <li><b>Password.</b> Your ALM project password.</li> <li><b>Authenticate on startup.</b> Authenticates your user information automatically, the next time you open the application. This option is available only if you selected <b>Reconnect to server on startup</b> above.</li> <li>•  . Authenticates your user information against the ALM server.  After your user information has been authenticated, the fields in the Authenticate user information area are displayed in read-only format. The Authenticate button changes to  .  You can log in to the same ALM server using a different user name by clicking <b>Change User</b>, entering a new user name and password, and then clicking <b>Authenticate</b> again.</li> </ul>
<b>Step 3: Login to Project</b>	<ul style="list-style-type: none"> <li><b>Domain.</b> The domain that contains the ALM project. Only those domains containing projects to which you have permission to connect to are displayed.</li> <li><b>Project.</b> Enter the ALM project name or select a project from the list. Only those projects that you have permission to connect to are displayed.</li> <li><b>Login to project on startup.</b> This option is only enabled when the <b>Authenticate on startup</b> check box is selected.</li> <li>•  /  . Logs into and out of the ALM project.</li> </ul>

## Upload Report to Test Lab Dialog Box

This dialog box enables you to upload an Analysis report to an ALM project's Test Lab module.



To access

Reports > Upload Report to Test Lab

User interface elements are described below:

UI Element	Description
<b>Step 1: Select the report file</b>	Allows you to select an Analysis report from the file system. You can select an HTML report, or Rich report in XML format.
<b>Step 2: Browse the test lab</b>	Allows you to select an location within the Test Lab module, for the report. <b>Note:</b> You must drill down to the level of a Run within the Test Lab module.
<b>Upload</b>	Begins the uploading of the report. If the uploading succeeds, the Analysis issues a message.

## Analysis Graphs

### Transaction Graphs

#### ***Transaction Graphs Overview***

During load test scenario execution, Vusers generate data as they perform transactions. Analysis enables you to generate graphs that show the transaction performance and status throughout script execution.


You can use additional Analysis tools such as merging and crossing results to understand your transaction performance graphs. You can also sort the graph information by transactions. For more information about working with Analysis, see section "["Introduction to Analysis" on page 1350](#)".

#### ***Average Transaction Response Time Graph***

This graph displays the average time taken to perform transactions during each second of the load test scenario run.

<b>Purpose</b>	If you have defined acceptable minimum and maximum transaction performance times, you can use this graph to determine whether the performance of the server is within the acceptable range.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) of each transaction
<b>Breakdown options</b>	<p><b>Transaction Breakdown</b></p> <p>You can view a breakdown of a transaction by right-clicking the transaction in the graph and selecting <b>Show Transaction Breakdown Tree</b>. In the Transaction Breakdown Tree, right-click the transaction you want to break down, and select <b>Break Down &lt;transaction name&gt;</b>. The Average Transaction Response Time graph displays data for the sub-transactions. For more details, see "<a href="#">"Transaction Breakdown Tree" on page 1462</a>".</p> <p><b>Web Page Breakdown</b></p> <p>To view a breakdown of the Web page(s) included in a transaction or sub-transaction, right-click it and select <b>Web Page Diagnostics for &lt;transaction name&gt;</b>. For more information on the Web Page Diagnostics graphs, see "<a href="#">"Web Page Diagnostics Graphs" on page 1502</a>".</p>
<b>Tips</b>	<p><b>Granularity</b></p> <p>This graph is displayed differently for each granularity. The lower the granularity, the more detailed the results. However, it may be useful to view the results with a higher granularity to study the overall Vuser behavior throughout the scenario. For example, using a low granularity, you may see intervals when no transactions were performed. However, by viewing the same graph with a higher granularity, you will see the graph for the overall transaction response time. For more information on setting the granularity, see "<a href="#">"How to Manage Graph Data" on page 1417</a>".</p> <p><b>Compare with Running Vusers</b></p> <p>You can compare the Average Transaction Response Time graph to the Running Vusers graph to see how the number of running Vusers affects the transaction performance time. For example, if the Average Transaction Response Time graph shows that performance time gradually improved, you can compare it to the Running Vusers graph to see whether the performance time improved due to a decrease in the Vuser load.</p>
<b>Note</b>	By default, only transactions that passed are displayed.
<b>See also</b>	<a href="#">"Transaction Graphs Overview" on the previous page</a>

Example




## Total Transactions per Second Graph

This graph displays the total number of transactions that passed, the total number of transactions that failed, and the total number of transactions that were stopped, during each second of a load test scenario run.

<b>Purpose</b>	Helps you determine the actual transaction load on your system at any given moment.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Total number of transactions performed during the scenario run.
<b>See also</b>	<a href="#">"Transaction Graphs Overview" on page 1459</a>

Example



## Transaction Breakdown Tree

The Transaction Breakdown Tree displays a tree view of the transactions and sub-transactions in the current session. From the tree, you can breakdown transactions and view the results of the breakdown in either the Average Transaction Response Time or Transaction Performance Summary graph.

<b>To access</b>	In either the Average Transaction Response Time or Transaction Performance Summary graph, right-click in the graph and select <b>Show Transaction Breakdown Tree</b> .
<b>Important information</b>	After you breakdown a transaction, you can return to the original transaction graph by reapplying the global filter ( <b>File &gt; Set Global Filter</b> ) or by undoing your breakdown actions using <b>Edit &gt; Undo Last Action</b> .

User interface elements are described below (unlabeled elements are shown in angle brackets):


UI Element	Description
<Right-click menu>	<ul style="list-style-type: none"><li>• <b>Break Down From Highest Level.</b> Displays data for the highest level hierarchical path of a transaction.</li><li>• <b>Break Down &lt;transaction name&gt;.</b> Displays data for the sub-transactions in the Average Transaction Response Time or Transaction Performance Summary graph.</li><li>• <b>Show Only &lt;transaction name&gt;.</b> Displays data only for the selected transaction/sub-transaction.</li><li>• <b>Web Page Diagnostics for &lt;page name&gt;.</b> Displays a breakdown of the Web page(s) included in a transaction or sub-transaction in the Web Page Diagnostics graphs. For details, see "<a href="#">Web Page Diagnostics Graphs</a>" on page 1502.</li></ul>

## ***Transactions per Second Graph***

This graph displays, for each transaction, the number of times it passed, failed, and stopped during each second of a load test scenario run.

<b>Purpose</b>	Helps you determine the actual transaction load on your system at any given moment.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of transactions performed during the scenario run.
<b>Tips</b>	<b>Compare with Average Transaction Response Time Graph</b> You can compare this graph to the Average Transaction Response Time graph in order to analyze the effect of the number of transactions on the performance time.
<b>See also</b>	<a href="#">"Transaction Graphs Overview"</a> on page 1459

### **Example**




## Transaction Performance Summary Graph

This graph displays the minimum, maximum and average performance time for all the transactions in the load test scenario.

X-axis	Name of the transaction.
Y-axis	Response time—rounded off to the nearest second—of each transaction.
Breakdown options	<p><b>Transaction Breakdown</b></p> <p>You can view breakdown of a transaction in the Transaction Performance Summary graph by right-clicking the transaction in the graph and selecting <b>Show Transaction Breakdown Tree</b>. In the Transaction Breakdown Tree, right-click the transaction you want to break down, and select <b>Break Down &lt;transaction name&gt;</b>. The Transaction Performance Summary graph displays data for the sub-transactions. For more details, see "<a href="#">"Transaction Breakdown Tree" on page 1462</a>.</p> <p><b>Web Page Breakdown</b></p> <p>To view a breakdown of the Web page(s) included in a transaction or sub-transaction, right-click it and select <b>Web Page Diagnostics for &lt;transaction name&gt;</b>. For more, see "<a href="#">"Web Page Diagnostics Graphs" on page 1502</a>.</p>
See also	<a href="#">"Transaction Graphs Overview" on page 1459</a>

Example




## Transaction Response Time (Distribution) Graph

This graph displays the distribution of the time taken to perform transactions in a load test scenario.

Purpose	If you have defined acceptable minimum and maximum transaction performance times, you can use this graph to determine whether the performance of the server is within the acceptable range.
X-axis	Transaction response time (rounded down to the nearest second).
Y-axis	Number of transactions executed during the scenario.
Tips	<b>Compare with Transaction Performance Summary Graph</b> If you compare it with the Transaction Performance Summary graph, you can see how the average performance was calculated.
Note	This graph can only be displayed as a bar graph.
See also	<a href="#">"Transaction Graphs Overview" on page 1459</a>

Example

In the following example, most of the transactions had a response time of less than 20 seconds.




## ***Transaction Response Time (Percentile) Graph***

This graph analyzes the percentage of transactions that were performed within a given time range.

<b>Purpose</b>	Helps you determine the percentage of transactions that met the performance criteria defined for your system. In many instances, you need to determine the percent of transactions with an acceptable response time. The maximum response time may be exceptionally long, but if most transactions have acceptable response times, the overall system is suitable for your needs.
<b>X-axis</b>	Percentage of the total number of transactions measured during the load test scenario run.
<b>Y-axis</b>	Maximum transaction response time (in seconds). <b>Note:</b> Analysis approximates the transaction response time for each available percentage of transactions. The y-axis values, therefore, may not be exact.
<b>Tips</b>	<b>Compare with Average Response Time Graph</b> It is recommended to compare the Percentile graph with a graph indicating average response time such as the Average Transaction Response Time graph. A high response time for several transactions may raise the overall average. However, if the transactions with a high response time occurred less than five percent of the time, that factor may be insignificant.
<b>See also</b>	<a href="#">"Transaction Graphs Overview" on page 1459</a>

### Example

In the following example, fewer than 20 percent of the tr\_matrix\_movie transactions had a response time less than 70 seconds.




## Transaction Response Time (Under Load) Graph

This graph is a combination of the Running Vusers and Average Transaction Response Time graphs and indicates transaction times relative to the number of Vusers running at any given point during the load test scenario.

<b>Purpose</b>	Helps you view the general impact of Vuser load on performance time and is most useful when analyzing a scenario with a gradual load.
<b>X-axis</b>	Number of running Vusers
<b>Y-axis</b>	Average response time (in seconds) of each transaction.
<b>See also</b>	<a href="#">"Transaction Graphs Overview" on page 1459</a>

Example




## Transaction Summary Graph

This graph summarizes the number of transactions in the load test scenario that failed, passed, stopped, and ended in error.

<b>X-axis</b>	Name of the transaction
<b>Y-axis</b>	Number of transactions performed during the scenario run.
<b>See also</b>	<a href="#">"Transaction Graphs Overview" on page 1459</a>

Example



## Flex Graphs

Flex graphs provide you with information about the performance of your Flex server. You use the Flex graphs to analyze the following data:


### Flex RTMP Throughput Graph

This graph shows the amount of throughput (in bytes) on the RTMP/T server during each second of the load test scenario run. The throughput represents the amount of data that the Vusers received from the server or sent to the server at any given second.

<b>Purpose</b>	Helps you evaluate the amount of load that Vusers generate, in terms of server throughput.
<b>X-axis</b>	Elapsed time since the start of the scenario run.
<b>Y-axis</b>	Throughput of the server in bytes
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.

Example

In the following example, the highest throughput is over 600,000 bytes during the thirty-fifth second of the scenario.




## Flex RTMP Other Statistics Graph

This graph shows various statistics about Flex RTMP Vusers.

<b>Purpose</b>	The graph shows the duration taken to perform various RTMP tasks.
<b>X-axis</b>	Elapsed time since the start of the scenario run.
<b>Y-axis</b>	Task duration (in milliseconds).

### Example

In the following example, the RTMP Handshake has a duration of seventy five milliseconds at the forty eighth second of the scenario.




## Flex RTMP Connections Graph

This graph shows the number of open RTMP connections at any time during the load test scenario run. The throughput represents the amount of data that the Vusers received from the server or sent to the server at any given second.

<b>Purpose</b>	This graph is useful in indicating when additional connections are needed. For example, if the number of connections reaches a plateau, and the transaction response time increases sharply, adding connections would probably cause a dramatic improvement in performance (reduction in the transaction response time).
<b>X-axis</b>	Elapsed time since the start of the scenario run.
<b>Y-axis</b>	Number of connections.

### Example

In the following example, between the forty-eighth second and the fifty-sixth second of the scenario there are eighty open connections.




## Flex Streaming Delivery Graph

This graph displays the total number of streams that were successfully delivered by the server. A successful delivery is indicated when the server initiates a "NetStream.Stop" message at the end of the requested stream.

<b>Purpose</b>	Helps you evaluate the amount of load that Vusers generate, in terms of server throughput.
<b>X-axis</b>	Elapsed time since the start of the scenario run.
<b>Y-axis</b>	Number of streams delivered

### Example

In the following example, the graph rises at a forty five degree angle, indicating a constant number of streams being delivered over time..




## Flex Average Buffering Time Graph

This graph displays the average buffering time for RTMP streams.

<b>Purpose</b>	Helps you evaluate the amount of load that Vusers generate, in terms of time spent for streams in the buffer.
<b>X-axis</b>	Elapsed time since the start of the scenario run.
<b>Y-axis</b>	Buffering time in milliseconds

### Example

In the following example, the buffering time reaches its lowest after 4 minutes and 32 seconds of the scenario before climbing up to a peak again. You should compare it to other graphs to see what happened at that time.



## Service Virtualization

### ***Service Virtualization Graphs Overview***

The Service Virtualization graphs are similar to the corresponding monitors used by the LoadRunner Controller. For details, see "["Service Virtualization Monitoring Overview" on page 1325](#)


### ***HP Service Virtualization Operations Graph***

This graph displays a summary for HP Service Virtualization - Operations.

<b>X-axis</b>	The elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	The number of resources used.
<b>Tips</b>	<ul style="list-style-type: none"><li>To isolate the measurement with the most problems, it may be helpful to sort the legend window according to the average number of resources used. To sort the legend by average, double-click the <b>Average</b> column heading.</li><li>To identify a measurement in the graph, you can select it. The corresponding line in the legend window is selected.</li></ul>
<b>Note</b>	To use this graph, you must first open a Service Virtualization project in the Controller scenario.
<b>See also</b>	<a href="#">"Web Page Diagnostics Graph" on page 1505</a>

## Example

Using the graph, you can track which resources were most problematic, and at which point(s) during the scenario the problem(s) occurred.




## HP Service Virtualization Services Graph

This graph displays a summary for HP Service Virtualization - Services.

<b>X-axis</b>	The elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	The number of resources used.
<b>Tips</b>	<ul style="list-style-type: none"><li>To isolate the measurement with the most problems, it may be helpful to sort the legend window according to the average number of resources used. To sort the legend by average, double-click the <b>Average</b> column heading.</li><li>To identify a measurement in the graph, you can select it. The corresponding line in the legend window is selected.</li></ul>
<b>Note</b>	To use this graph, you must first open a Service Virtualization project in the Controller scenario.
<b>See also</b>	<a href="#">"Web Page Diagnostics Graph" on page 1505</a>

## Example

Using the graph, you can track which resources were most problematic, and at which point(s) during the scenario the problem(s) occurred.



## Vuser Graphs

### ***Vuser Graphs Overview***

During load test scenario execution, Vusers generate data as they perform transactions. The Vuser graphs let you determine the overall behavior of Vusers during the scenario. They display the Vuser states, the number of Vusers that completed the script, and rendezvous statistics. Use these graphs in conjunction with Transaction graphs to determine the effect of the number of Vusers on transaction response time. For more information about Transaction graphs, see "["Transaction Graphs" on page 1459.](#)

### ***Rendezvous Graph (Vuser Graphs)***


During a scenario run, you can instruct multiple Vusers to perform tasks simultaneously by using **rendezvous points**. A rendezvous point creates intense user load on the server and enables LoadRunner to measure server performance under load. For more information about using rendezvous points, see the *HP Virtual User Generator User Guide*.

This graph indicates when Vusers were released from rendezvous points, and how many Vusers were released at each point.

<b>Purpose</b>	Helps you understand transaction performance times.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of Vusers that were released from the rendezvous.

<b>Tips</b>	<b>Compare to Average Transaction Response Time graph</b> If you compare the Rendezvous graph to the Average Transaction Response Time graph, you can see how the load peak created by a rendezvous influences transaction times.
<b>See also</b>	<a href="#">"Vuser Graphs Overview" on the previous page</a>

### Example




## Running Vusers Graph

This graph displays the number of Vusers that executed Vuser scripts and their status during each second of the test.

<b>Purpose</b>	Helps you determine the Vuser load on your server at any given moment.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of Vusers in the scenario.
<b>Note</b>	By default, this graph only shows the Vusers with a <b>Run</b> status. To view another Vuser status, set the filter conditions to the desired status. For more information, see <a href="#">"Filtering and Sorting Graph Data" on page 1394</a> .
<b>See also</b>	<a href="#">"Vuser Graphs Overview" on the previous page</a>

### Example




## Vuser Summary Graph

This graph displays a summary of Vuser performance.

<b>Purpose</b>	Lets you view the number of Vusers that successfully completed the load test scenario run relative to those that did not.
<b>Note</b>	This graph may only be viewed as a pie.
<b>See also</b>	<a href="#">"Vuser Graphs Overview" on page 1475</a>

### Example



## Error Graphs

### ***Error Graphs Overview***


During load test scenario execution, Vusers may not complete all transactions successfully. The Error graphs let you view information about the transactions that failed, stopped, or ended in errors. Using the Error graphs, you can view a summary of errors that occurred during the scenario and the average number of errors that occurred per second.

### ***Errors per Second (by Description) Graph***

This graph displays the average number of errors that occurred during each second of the load test scenario run, grouped by error description. The error description is displayed in the legend.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of errors.
<b>See also</b>	<a href="#">"Error Graphs Overview" above</a>

#### **Example**




## Errors per Second Graph

This graph displays the average number of errors that occurred during each second of the load test scenario run, grouped by error code.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of errors.
<b>See also</b>	<a href="#">"Error Graphs Overview" on the previous page</a>

### Example




## Error Statistics (by Description) Graph

This graph displays the number of errors that accrued during load test scenario execution, grouped by error description. The error description is displayed in the legend.

Note	This graph may only be viewed as a pie.
See also	<a href="#">"Error Graphs Overview" on page 1478</a>

### Example




## Error Statistics Graph

This graph displays the number of errors that accrued during load test scenario execution, grouped by error code.

<b>Note</b>	This graph may only be viewed as a pie.
<b>See also</b>	<a href="#">"Error Graphs Overview" on page 1478</a>

### Example

In the following example, out of a total of 178 errors that occurred during the scenario run, the second error code displayed in the legend occurred twelve times, comprising 6.74% of the errors.




## **Total Errors per Second Graph**

This graph displays the average number of errors that occurred during each second of the load test scenario run. (complete: add sentence about being sum of all errors)

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of errors.
<b>See also</b>	<a href="#">"Error Graphs Overview" on page 1478</a>

## Example



## Web Resources Graphs

### ***Web Resources Graphs Overview***

Web Resource graphs provide you with information about the performance of your Web server. You use the Web Resource graphs to analyze the following data:

- Throughput on the Web server
- The number of hits per second
- The number of HTTP responses per second
- The HTTP status codes returned from the Web server
- The number of downloaded pages per second
- The number of server retries per second
- A summary of the server retries during the load test scenario
- The number of open TCP/IP connections
- The number of TCP/IP connections per second
- The number of new and reused SSL connections opened per second


### ***Hits per Second Graph***

This graph shows the number of HTTP requests made by Vusers to the Web server during each second of the load test scenario run.

<b>Purpose</b>	Helps you evaluate the amount of load Vusers generate, in terms of the number of hits.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of hits on the server.
<b>Tips</b>	<b>Compare to Average Transaction Response Time graph</b> You can compare this graph to the Average Transaction Response Time graph to see how the number of hits affects transaction performance.
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on the previous page</a>

### Example

In the following example, the most hits per second took place during the fifty-fifth second of the scenario.




## Throughput Graph

This graph shows the amount of throughput on the server during each second of the load test scenario run. Throughput is measured in bytes or megabytes and represents the amount of data that the Vusers received from the server at any given second. To view throughput in megabytes, use the **Throughput (MB)** graph.

<b>Purpose</b>	Helps you evaluate the amount of load that Vusers generate, in terms of server throughput.
<b>X-axis</b>	Elapsed time since the start of the scenario run.
<b>Y-axis</b>	Throughput of the server, in bytes or megabytes.
<b>Tips</b>	<b>Compare to Average Transaction Response Time graph</b> You can compare this graph to the Average Transaction Response Time graph to see how the throughput affects transaction performance.
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on page 1483</a>

### Example

In the following example, the highest throughput is 193,242 bytes during the fifty-fifth second of the scenario.




## HTTP Status Code Summary Graph

This graph shows the number of HTTP status codes returned from the Web server during the load test scenario run, grouped by status code. HTTP status codes indicate the status of HTTP requests, for example, "the request was successful", "the page was not found".

<b>Tips</b>	<b>Locate scripts which generated error codes</b>
	Use this graph together with the HTTP Responses per Second graph to locate those scripts which generated error codes.
<b>Note</b>	This graph can only be viewed as a pie.

### Example

In the following example, the graph shows that only the HTTP status codes 200 and 302 were generated. Status code 200 was generated 1,100 times, and status code 302 was generated 125 times.



## HTTP Status Codes

The following table displays a list of HTTP status codes:

Code	Description
200	OK
201	Created
202	Accepted
203	Non-Authoritative Information

, continued

<b>Code</b>	<b>Description</b>
204	No Content
205	Reset Content
206	Partial Content
300	Multiple Choices
301	Moved Permanently
302	Found
303	See Other
304	Not Modified
305	Use Proxy
307	Temporary Redirect
400	Bad Request
401	Unauthorized
402	Payment Required
403	Forbidden
404	Not Found
405	Method Not Allowed
406	Not Acceptable
407	Proxy Authentication Required
408	Request Timeout
409	Conflict
410	Gone
411	Length Required
412	Precondition Failed
413	Request Entity Too Large
414	Request - URI Too Large
415	Unsupported Media Type
416	Requested range not satisfiable

, continued

Code	Description
417	Expectation Failed
500	Internal Server Error
501	Not Implemented
502	Bad Gateway
503	Service Unavailable
504	Gateway Timeout
505	HTTP Version not supported

For more information on the above status codes and their descriptions, see <http://www.w3.org>.


## HTTP Responses per Second Graph

This graph shows the number of HTTP status codes returned from the Web server during each second of the load test scenario run, grouped by status code. HTTP status codes indicate the status of HTTP requests, for example, "the request was successful", "the page was not found".

X-axis	Elapsed time since the start of the run.
Y-axis	Number of HTTP responses per second.
Tips	<b>Locate scripts which generated error codes</b> You can group the results shown in this graph by script (using the "Group By" function) to locate scripts which generated error codes. For more information on the "Group By" function, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394.
See also	<ul style="list-style-type: none"><li><a href="#">"Web Resources Graphs Overview"</a> on page 1483</li><li><a href="#">"HTTP Status Codes"</a> on page 1486</li></ul>

### Example

In the following example, the greatest number of **200** status codes, 60, was generated in the fifty-fifth second of the scenario run. The greatest number of **302** codes, 8.5, was generated in the fiftieth second of the scenario run.



## Pages Downloaded per Second Graph


This graph shows the number of Web pages downloaded from the server during each second of the load test scenario run.

Like the Throughput graph, the Pages Downloaded per Second graph represents the amount of data that the Vusers received from the server at any given second. However, the Throughput graph takes into account each resource and its size (for example, the size of each .gif file, the size of each Web page). The Pages Downloaded per Second graph takes into account only the number of pages.

<b>Purpose</b>	Helps you evaluate the amount of load Vusers generate, in terms of the number of pages downloaded.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of Web pages downloaded from the server.
<b>Note</b>	To view the Pages Downloaded per Second graph, you must select <b>Pages per second (HTML Mode only)</b> from the run time settings Preferences tab before running your scenario.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on page 1483</a>


### Example 1

In the following example, the greatest number of pages downloaded per second, about 7, occurred in the fiftieth second of the scenario run.



### Example 2

In the following example, the Throughput graph is merged with the Pages Downloaded per Second graph. It is apparent from the graph that throughput is not completely proportional to the number of pages downloaded per second. For example, between 10 and 25 seconds into the scenario run, the number of pages downloaded per second increased while the throughput decreased.



## Retries per Second Graph


This graph displays the number of attempted server connections during each second of the load test scenario run. A server connection is retried when:

- the initial connection was unauthorized
- proxy authentication is required
- the initial connection was closed by the server
- the initial connection to the server could not be made
- when the server was initially unable to resolve the load generator's IP address

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of server retries per second.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on page 1483</a>

### Example

In the following example, the graph shows that during the first second of the scenario, the number of retries was 0.4, whereas in the fifth second of the scenario, the number of retries per second rose to 0.8.




## **Retries Summary Graph**

This graph shows the number of attempted server connections during the load test scenario run, grouped by the cause of the retry.

<b>Tips</b>	<b>Determine when server retries were attempted</b> Use this graph together with the Retries per Second graph to determine at what point during the scenario the server retries were attempted.
<b>Note</b>	This graph may only be viewed as a pie.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on page 1483</a>

## Example


In the following example, the graph shows that the server's inability to resolve the load generator's IP address was the leading cause of server retries during the scenario run.



# **Connections Graph**

This graph shows the number of open TCP/IP connections (y-axis) at each point in time of the load test scenario (x-axis). Depending on the emulated browser type, each Vuser may open several simultaneous connections per Web server.

<b>Purpose</b>	This graph is useful in indicating when additional connections are needed. For example, if the number of connections reaches a plateau, and the transaction response time increases sharply, adding connections would probably cause a dramatic improvement in performance (reduction in the transaction response time).
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Open TCP/IP connections.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on page 1483</a>




## ***Connections per Second Graph***

This graph shows the number of new TCP/IP connections (y-axis) opened and the number of connections that are shut down for each second of the load test scenario (x-axis).

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	TCP/IP connections per second.

<b>Tips</b>	<b>New connections versus hits per second:</b> The number of new connections should be a small fraction of the number of hits per second, because new TCP/IP connections are very expensive in terms of server, router and network resource consumption. Ideally, many HTTP requests should use the same connection, instead of opening a new connection for each request.
<b>See also</b>	<a href="#">"Web Resources Graphs Overview" on page 1483</a>




## SSLs per Second Graph

This graph shows the number of new and reused SSL Connections (y-axis) opened in each second of the load test scenario (x-axis). An SSL connection is opened by the browser after a TCP/IP connection has been opened to a secure server.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Number of SSL Connections

Tips	<b>Reduce SSL connections</b>
	<p>Creating a new SSL connection entails heavy resource consumption. Therefore, you should try to open as few new SSL connections as possible. Once you've established an SSL connection, you should reuse it. There should be no more than one new SSL connection per Vuser.</p>
	<p>In cases where you reset TCP connections between iterations (<b>VuGen Run-Time Settings &gt; Browser Emulation node &gt; Simulate a new user on each iteration</b>), you should have no more than one new SSL connection per iteration.</p>
See also	<a href="#">"Web Resources Graphs Overview" on page 1483</a>

### Example



## User-Defined Data Point Graphs

### *User-Defined Data Point Graphs Overview*

The User-Defined Data Point graphs display the values of user-defined data points. You define a data point in your Vuser script by inserting an `Ir_user_data_point` function at the appropriate place (`user_data_point` for GUI Vusers and `Ir.user_data_point` for Java Vusers).

```
Action1()
{
    lr_think_time(1);
    lr_user_data_point ("data_point_1",1);
    lr_user_data_point ("data_point_2",2);
    return 0;
}
```

For Vuser protocols that support the graphical script representations such as Web and Oracle NCA, you insert a data point as a User Defined step. Data point information is gathered each time the script executes the function or step. For more information about data points, refer to the Function Reference.

Data points, like other Analysis data, are aggregated every few seconds, resulting in less data points shown on the graph than actually recorded. For more information, see "["Changing the Granularity of the Data" on page 1414](#)".


## ***Data Points (Average) Graph***

This graph shows the average values that were recorded for user-defined data points during the load test scenario run.

<b>Purpose</b>	This graph is typically used in cases where the actual value of the measurement is required. Suppose that each Vuser monitors CPU utilization on its machine and records it as a data point. In this case, the actual recorded value of CPU utilization is required. The Average graph displays the average value recorded throughout the scenario.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The average values of the recorded data point statements.
<b>See also</b>	<a href="#">"User-Defined Data Point Graphs Overview" on the previous page</a>

### **Example**

In the following example, the CPU utilization is recorded as the data point `user_data_point_val_1`. It is shown as a function of the elapsed scenario time.



## Data Points (Sum) Graph


This graph shows the sum of the values for user-defined data points throughout the load test scenario run.

This graph typically indicates the total amount of measurements which all Vusers are able to generate. For example, suppose only a certain set of circumstances allow a Vuser to call a server. Each time it does, a data point is recorded. In this case, the Sum graph displays the total number of times that Vusers call the function.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The sum of the recorded data point values.
<b>See also</b>	<a href="#">"User-Defined Data Point Graphs Overview" on page 1495</a>

### Example

In the following example, the call to the server is recorded as the data point `user_data_point_val_1`. It is shown as a function of the elapsed scenario time.




## Network Monitor Graphs

### ***Network Monitor Graphs Overview***

Network configuration is a primary factor in the performance of applications and Web systems. A poorly designed network can slow client activity to unacceptable levels. In an application, there are many network segments. A single network segment with poor performance can affect the entire application.

The following diagram shows a typical network. To go from the server machine to the Vuser machine, data must travel over several segments.



To measure network performance, the Network monitor sends packets of data across the network. When a packet returns, the monitor calculates the time it takes for the packet to go to the requested node and return.

The Network Sub-Path Time graph displays the delay from the source machine to each node along the path. The Network Segment Delay graph displays the delay for each segment of the path. The Network Delay Time graph displays the delay for the complete path between the source and destination machines.

Using the Network Monitor graphs, you can determine whether the network is causing a bottleneck. If the problem is network-related, you can locate the problematic segment so that it can be fixed.

In order for Analysis to generate Network monitor graphs, you must activate the Network monitor before executing the load test scenario. In the Network monitor settings, you specify the path you want to monitor. For information about setting up the Network monitor, refer to the *HP LoadRunner Controller User Guide*.

## Network Delay Time Graph


This graph shows the delays for the complete path between the source and destination machines (for example, the database server and Vuser load generator). The graph maps the delay as a function of the elapsed load test scenario time.

Each path defined in the Controller is represented by a separate line with a different color in the graph.

X-axis	Elapsed time since the start of the run.
Y-axis	Network delay time.
Tips	<b>Merge graphs to determine network bottleneck</b> You can merge various graphs to determine if the network is a bottleneck. For example, using the Network Delay Time and Running Vusers graphs, you can determine how the number of Vusers affects the network delay.
See also	<a href="#">"Network Monitor Graphs Overview" on the previous page</a>

### Example

In the following example of a merged graph, the network delays are compared to the running Vusers. The graph shows that when all 10 Vusers were running, a network delay of 22 milliseconds occurred, implying that the network may be overloaded.




## Network Segment Delay Graph

This graph shows the delay for each segment of the path according to the elapsed load test scenario time. Each segment is displayed as a separate line with a different color.

X-axis	Elapsed time since the start of the run.
Y-axis	Network delay time.
Note	The segment delays are measured approximately, and do not add up to the network path delay which is measured exactly. The delay for each segment of the path is estimated by calculating the delay from the source machine to one node and subtracting the delay from the source machine to another node. For example, the delay for segment B to C is calculated by measuring the delay from the source machine to point C, and subtracting the delay from the source machine to point B.
See also	<a href="#">"Network Monitor Graphs Overview" on page 1498</a>

### Example

In the following example, four segments are shown. The graph indicates that one segment caused a delay of 70 seconds in the sixth minute.




## Network Sub-Path Time Graph

This graph displays the delay from the source machine to each node along the path according to the elapsed load test scenario time. Each segment is displayed as a separate line with a different color.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Network delay time.
<b>Note</b>	The delays from the source machine to each of the nodes are measured concurrently, yet independently. It is therefore possible that the delay from the source machine to one of the nodes could be greater than the delay for the complete path between the source and destination machines.
<b>See also</b>	<a href="#">"Network Monitor Graphs Overview" on page 1498</a>

### Example

In the following example, four segments are shown. The graph indicates that one segment caused a delay of 70 milliseconds in the sixth minute.



## Web Page Diagnostics Graphs

### ***Web Page Diagnostics Tree View Overview***

The Web Page Diagnostics tree view displays a tree view of the transactions, sub-transactions, and Web pages for which you can view Web Page Diagnostics graphs. For more information about Web Page Diagnostics graphs, see "["Web Page Diagnostics Graph" on page 1505](#)".


The Web Page Diagnostics graphs enable you to assess whether transaction response times were affected by page content. Using the Web Page Diagnostics graphs, you can analyze problematic elements—for example, images that download slowly, or broken links—of a Web site.

### ***Web Page Diagnostics Graphs Overview***

Web Page Diagnostics graphs provide you with performance information for each monitored Web page in your script. You can view the download time of each page in the script and its components, and identify at what point during download time problems occurred. In addition, you can view the relative download time and size of each page and its components. Analysis displays both average download time and download time over time data.

You correlate the data in the Web Page Diagnostics graphs with data in the Transaction Performance Summary and Average Transaction Response Time graphs in order to analyze why and where problems are occurring, and whether the problems are network- or server-related.

The following diagram illustrates the sequence of events from the time an HTTP request is sent:



**Note:** Because server time is being measured from the client, network time may influence this measurement if there is a change in network performance from the time the initial HTTP request is sent until the time the first buffer is sent. The server time displayed, therefore, is estimated server time and may be slightly inaccurate.

You begin analyzing the Transaction Performance Summary and Average Transaction Response Time graphs with the Web Page Diagnostics graph, which displays the average download time (in seconds) for each monitored Web page during each second of the load test scenario run. The x-axis represents the elapsed time from the beginning of the scenario run. The y-axis represents the average download time (in seconds) for each Web page.

In order for Analysis to generate Web Page Diagnostics graphs, you must enable the Web Page Diagnostics feature in the Controller before running your scenario.


1. From the Controller menu, choose **Diagnostics > Configuration** and select the **Enable the following diagnostics** check box.
2. Under **Offline Diagnostics**, click **Enable** to the right of **Web Page Diagnostics (Max. Vuser Sampling: 10%)**.

**Note:** It is recommended that, in VuGen, you select **HTML-based script** in the Recording tab of the Recording Options dialog box.

For more information on recording scripts, refer to the VuGen section in the *LoadRunner User Guide*.

## How to View the Breakdown of a Transaction

The Web Page Diagnostics graphs are most commonly used to analyze a problem detected in the Transaction Performance Summary or Average Transaction Response Time graphs. For example, the Average Transaction Response Time graph below demonstrates that the average transaction response time for the trans1 transaction was high.



Using the Web Page Diagnostics graphs, you can pinpoint the cause of the delay in response time for the trans1 transaction.

This task describes how to breakdown a transaction.

1. Right-click **trans1** and select **Web Page Diagnostics for trans1**. The Web Page Diagnostics graph opens and the Web Page Diagnostics tree appear. An icon appears next to the page name indicating the page content. See "[Web Page Diagnostics Content Icons](#)" on the next page.
2. In the Web Page Diagnostics tree, right-click the problematic page you want to break down, and select **Break Down <component name>**. Alternatively, select a page in the **Select Page to Break Down** box that appears under the Web Page Diagnostics graph. The Web Page Diagnostics graph for that page appears.

**Note:** You can open a browser displaying the problematic page by right-clicking the page in the Web Page Diagnostics tree and selecting **View page in browser**.

3. Select one of the following available breakdown options:
  - **Download Time.** Displays a table with a breakdown of the selected page's download time. The size of each page component (including the component's header) is displayed. See the

"[Page Download Time Breakdown Graph](#)" on page [1510](#) for more information about this display.

- **Component (Over Time).** Displays the "[Page Component Breakdown \(Over Time\) Graph](#)" on page [1509](#) for the selected Web page.
- **Download Time (Over Time).** Displays the "[Page Download Time Breakdown \(Over Time\) Graph](#)" on page [1512](#) for the selected Web page.
- **Time to First Buffer (Over Time).** Displays the "[Time to First Buffer Breakdown \(Over Time\) Graph](#)" on page [1517](#) for the selected Web page.

To display the graphs in full view, click the  button. You can also access these graphs, as well as additional Web Page Diagnostics graphs, from the Open a New Graph dialog box.

## Web Page Diagnostics Content Icons

The following icons appear in the Web Page Diagnostics tree. They indicate the HTTP content of the page.

Name	Description
	<b>Transaction.</b> Specifies that the ensuing content is part of the transaction.
	<b>Page Content.</b> Specifies that the ensuing content, which may include text, images, and so on, is all part of one logical page.
	<b>Text content.</b> Textual information. Plain text is intended to be displayed as-is. Includes HTML text and style sheets.
	<b>Multipart content.</b> Data consisting of multiple entities of independent data types.
	<b>Message content.</b> An encapsulated message. Common subtypes are news, or external-body which specifies large bodies by reference to an external data source.
	<b>Application content.</b> Some other kind of data, typically either uninterpreted binary data or information to be processed by an application. An example subtype is Postscript data.
	<b>Image content.</b> Image data. Two common subtypes are the jpeg and gif format.
	<b>Resource content.</b> Other resources not listed above. Also, content that is defined as "not available" is likewise included.

## Web Page Diagnostics Graph


The Web Page Diagnostics graph provides you with performance information for each monitored Web page in your script. You can view the download time of each page in the script and its

components, and identify at what point during download time problems occurred. In addition, you can view the average download time of each page and its components.

<b>Purpose</b>	This graph enables you to determine at what point during scenario execution a network or server problem occurred, that may have affected access to the Web page.
<b>X-axis</b>	Elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	The download time (in seconds) for each Web page in the download process.
<b>Tips</b>	<ul style="list-style-type: none"> <li>Choose a page in the <b>Select Page to Break Down</b> drop-down box.</li> <li>To isolate the most problematic components, you can sort the legend window according to the average number of seconds taken to download a component. To sort the legend by average, double-click the <b>Average</b> column heading.</li> </ul>
<b>Diagnostic Options</b>	<p>You can choose one of the following options to drill down on the results. For sample graphs, see below.</p> <ul style="list-style-type: none"> <li><b>Download Time</b> - as a bar graph</li> <li><b>Component (Over Time)</b> - as a line graph</li> <li><b>Download Time (Over Time)</b> - as an area graph</li> <li><b>Time to First Buffer (Over Time)</b> - as an area graph</li> </ul>
<b>See also</b>	<a href="#">"Web Page Diagnostics Tree View Overview" on page 1502</a>


### Example

This graph enables you to monitor the download time during the scenario execution, to determine at what point network or server problems occurred.




### Download Time

In the following example, the download time for the **itinerary.pl** page was the greatest during the **Receive** stage.




## Component(Over Time)

In the following example, the download time for the **itinerary.pl** component was the greatest at approximately 8:40 into the scenario.




## Download Time (Over Time)

The following graph shows the download time for the **itinerary.pl** page as an area graph.



## Time to First Buffer (Over Time)

In the following example, the download time for the **splash\_itinerary.gif** file was the greatest approximately 8:40 into the scenario.




## Page Component Breakdown Graph

This graph displays the average download time (in seconds) for each Web page and its components.

<b>Breakdown options</b>	To ascertain which components caused the delay in download time, you can break down the problematic URL by double-clicking it in the Web Page Diagnostics tree.
<b>Tips</b>	To isolate problematic components, it may be helpful to sort the legend according to the average number of seconds taken to download a component. To sort the legend by average, click the <b>Graph's Average</b> column.
<b>Note</b>	The graph can only be viewed as a pie.
<b>See also</b>	<a href="#">"Web Page Diagnostics Graphs Overview" on page 1502</a>


### Example

The following graph demonstrates that the main cnn.com URL took 28.64% of the total download time, compared to 35.67% for the www.cnn.com/WEATHER component.



### Example

The graph shows that the main cnn.com/WEATHER component took the longest time to download (8.98% of the total download time).




## Page Component Breakdown (Over Time) Graph

This graph displays the average response time (in seconds) for each Web page and its components during each second of the load test scenario run.

X-axis	The elapsed time from the beginning of the scenario run.
Y-axis	The average response time (in seconds) for each component.
Tips	<ul style="list-style-type: none"><li>To isolate the most problematic components, it may be helpful to sort the legend window according to the average number of seconds taken to download a component. To sort the legend by average, double-click the <b>Average</b> column heading.</li><li>To identify a component in the graph, you can select it. The corresponding line in the legend window is selected.</li></ul>
See also	<a href="#">"Web Page Diagnostics Graphs Overview" on page 1502</a>


### Example

The following graph demonstrates that the response time for Satellite\_Action1\_963 was significantly greater, throughout the scenario, than the response time for main\_js\_Action1\_938.



### Example

Using the graph, you can track which components of the main component were most problematic, and at which point(s) during the scenario the problem(s) occurred.




## Page Download Time Breakdown Graph

This graph displays a breakdown of each page component's download time.

<b>Purpose</b>	Enables you to determine whether slow response times are being caused by network or server errors during Web page download.
<b>Breakdown options</b>	For breakdown options, see "Page Download Time Breakdown Graph Breakdown Options" on page 1514.  <b>Note:</b> Each measurement displayed on the page level is the sum of that measurement recorded for each page component. For example, the Connection Time for www.cnn.com is the sum of the Connection Time for each of the page's components.
<b>See also</b>	<a href="#">"Web Page Diagnostics Graphs Overview" on page 1502</a>

### Example


The Page Download Time Breakdown graph demonstrates that receive time, connection time, and first buffer time accounted for a large portion of the time taken to download the main cnn.com URL.



### Example

If you break the cnn.com URL down further, you can isolate the components with the longest download time, and analyze the network or server problems that contributed to the delay in response time.

Breaking down the cnn.com URL demonstrates that for the component with the longest download time (the www.cnn.com component), the receive time accounted for a large portion of the download time.



## Page Download Time Breakdown (Over Time) Graph

The graph displays a breakdown of each page component's download time during each second of the load test scenario run.


<b>Purpose</b>	This graph enables you to determine at what point during scenario execution network or server problems occurred.
<b>X-axis</b>	Elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	Time (in seconds) taken for each step in the download process.
<b>Tips</b>	To isolate the most problematic components, you can sort the legend window according to the average number of seconds taken to download a component. To sort the legend by average, double-click the <b>Average</b> column heading.
<b>Notes</b>	<ul style="list-style-type: none"> <li>Each measurement displayed on the page level is the sum of that measurement recorded for each page component. For example, the Connection Time for www.cnn.com is the sum of the Connection Time for each of the page's components.</li> <li>When the Page Download Time Breakdown (Over Time) graph is selected from the Web Page Diagnostics graph, it appears as an area graph.</li> </ul>

**See also**

["Web Page Diagnostics Graphs Overview" on page 1502](#)


**Example**

This graph enables you to determine at what point during scenario execution network or server problems occurred.



**Example**

In the example in the previous section, it is apparent that `cnn.com` was the most problematic component. If you examine the `cnn.com` component, the Page Download Time Breakdown (Over Time) graph demonstrates that **First Buffer** and **Receive** time remained high throughout the scenario, and that **DNS Resolution** time decreased during the scenario.



## Page Download Time Breakdown Graph Breakdown Options

The Page Download Time Breakdown graph breaks down each component by DNS resolution time, connection time, time to first buffer, SSL handshaking time, receive time, FTP authentication time, client time, and error time.

These breakdowns are described below:

Name	Description
DNS Resolution	Displays the amount of time needed to resolve the DNS name to an IP address, using the closest DNS server. The DNS Lookup measurement is a good indicator of problems in DNS resolution, or problems with the DNS server.
Connection	Displays the amount of time needed to establish an initial connection with the Web server hosting the specified URL. The connection measurement is a good indicator of problems along the network. It also indicates whether the server is responsive to requests.
First Buffer	Displays the amount of time that passes from the initial HTTP request (usually GET) until the first buffer is successfully received back from the Web server. The first buffer measurement is a good indicator of Web server delay as well as network latency.  <b>Note:</b> Since the buffer size may be up to 8K, the first buffer might also be the time it takes to completely download the element.

Name	Description
SSL Handshaking	<p>Displays the amount of time taken to establish an SSL connection (includes the client hello, server hello, client public key transfer, server certificate transfer, and other—partially optional—stages). After this point, all the communication between the client and server is encrypted.</p> <p>The SSL Handshaking measurement is only applicable for HTTPS communications.</p>
Receive	<p>Displays the amount of time that passes until the last byte arrives from the server and the downloading is complete.</p> <p>The Receive measurement is a good indicator of network quality (look at the time/size ratio to calculate receive rate).</p>
FTP Authentication	<p>Displays the time taken to authenticate the client. With FTP, a server must authenticate a client before it starts processing the client's commands.</p> <p>The FTP Authentication measurement is only applicable for FTP protocol communications.</p>
Client Time	Displays the average amount of time that passes while a request is delayed on the client machine due to browser think time or other client-related delays.
Error Time	Displays the average amount of time that passes from the moment an HTTP request is sent until the moment an error message (HTTP errors only) is returned.

## Time to First Buffer Breakdown Graph

This graph displays each Web page component's relative server/network time (in seconds) for the period of time until the first buffer is successfully received back from the Web server.


**Note:** This graph is only relevant when the load generator does not use a proxy to connect to the application under test. If the load generator is connected through a proxy, this graph will only show the proxy latency—not the AUT latency.

Purpose	If the download time for a component is high, you can use this graph to determine whether the problem is server- or network-related.
X-axis	Specifies the name of the component.
Y-axis	Shows the average network/server time (in seconds) for each component.

<b>Measurements</b>	<ul style="list-style-type: none"><li>Network time is defined as the average amount of time that passes from the moment the first HTTP request is sent until receipt of ACK.</li><li>Server time is defined as the average amount of time that passes from the receipt of ACK of the initial HTTP request (usually GET) until the first buffer is successfully received back from the Web server.</li></ul>
<b>Note</b>	<ul style="list-style-type: none"><li>Each measurement displayed on the page level is the sum of that measurement recorded for each page component. For example, the network time for www.cnn.com is the sum of the network time for each of the page's components.</li><li>Because server time is being measured from the client, network time may influence this measurement if there is a change in network performance from the time the initial HTTP request is sent until the time the first buffer is sent. The server time displayed, therefore, is estimated server time and may be slightly inaccurate.</li><li>The graph can only be viewed as a bar graph.</li></ul>
<b>See also</b>	<a href="#">"Web Page Diagnostics Graphs Overview" on page 1502</a>


### Example

In the following example it is apparent that network time is greater than server time.



### Example

In the following example shows that you can break the main cnn.com URL down further to view the time to first buffer breakdown for each of its components. It is apparent that for the main cnn.com component (the first component on the right), the time to first buffer breakdown is almost all network time.




## Time to First Buffer Breakdown (Over Time) Graph

This graph displays each Web page component's server and network time (in seconds) during each second of the load test scenario run, for the period of time until the first buffer is successfully received back from the Web server.

**Note:** This graph is only relevant when the load generator does not use a proxy to connect to the application under test. If the load generator is connected through a proxy, this graph will only show the proxy latency—not the AUT latency.


Purpose	You can use this graph to determine when during the scenario run a server- or network-related problem occurred.
X-axis	Elapsed time from the beginning of the scenario run.
Y-axis	Average network or server time (in seconds) for each component.
Measurements	<ul style="list-style-type: none"><li>Network time is defined as the average amount of time that passes from the moment the first HTTP request is sent until receipt of ACK.</li><li>Server time is defined as the average amount of time that passes from the receipt of ACK of the initial HTTP request (usually GET) until the first buffer is successfully received back from the Web server.</li></ul> <p><b>Note:</b> Because server time is being measured from the client, network time may influence this measurement if there is a change in network performance from the time the initial HTTP request is sent until the time the first buffer is sent. The server time displayed, therefore, is estimated server time and may be slightly inaccurate.</p>

<b>Note</b>	<ul style="list-style-type: none"><li>Each measurement displayed on the page level is the sum of that measurement recorded for each page component. For example, the network time for www.hp.com is the sum of the network time for each of the page's components.</li><li>When the Time to First Buffer Breakdown (Over Time) graph is selected from the Web Page Diagnostics graph, it appears as an area graph.</li></ul>
<b>See also</b>	<a href="#">"Web Page Diagnostics Graphs Overview" on page 1502</a>



## Example

In the following example you can break the main cnn.com URL down further to view the time to first buffer breakdown for each of its components.




## Client Side Breakdown (Over Time) Graph

This graph displays the client side breakdown of each transaction during each second of the load test scenario run.

<b>X-axis</b>	The elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	The average response time (in seconds) for each transaction.
<b>Tips</b>	<ul style="list-style-type: none"><li>To isolate the most problematic transactions, it may be helpful to sort the legend window according to the average number of seconds taken for the transaction to run. To sort the legend by average, double-click the <b>Average</b> column heading.</li><li>To identify a transaction in the graph, you can select it. The corresponding line in the legend window is selected.</li></ul>
<b>See also</b>	<a href="#">"Web Page Diagnostics Graph" on page 1505</a>

### Example

Using the graph, you can track which transactions on the client side were most problematic, and at which point(s) during the scenario the problem(s) occurred.




## Client Side Java Script Breakdown (Over Time) Graph

This graph displays the client side breakdown of each JavaScript transaction during each second of the load test scenario run.

X-axis	The elapsed time from the beginning of the scenario run.
Y-axis	The average response time (in seconds) for each transaction.
Tips	<ul style="list-style-type: none"><li>To isolate the most problematic transactions, it may be helpful to sort the legend window according to the average number of seconds taken for the transaction to run. To sort the legend by average, double-click the <b>Average</b> column heading.</li><li>To identify a transaction in the graph, you can select it. The corresponding line in the legend window is selected.</li></ul>
See also	<a href="#">"Web Page Diagnostics Graph" on page 1505</a>

### Example

Using the graph, you can track which transactions on the client side were most problematic, and at which point(s) during the scenario the problem(s) occurred.




## Downloaded Component Size Graph

This graph displays the size of each Web page component.

<b>Note</b>	<ul style="list-style-type: none"><li>The Web page size is a sum of the sizes of each of its components.</li><li>The Downloaded Component Size graph can only be viewed as a pie graph.</li></ul>
<b>See also</b>	<a href="#">"Web Page Diagnostics Graphs Overview" on page 1502</a>


### Example

In the following example the `www.cnn.com/WEATHER` component is 39.05% of the total size, whereas the main `cnn.com` component is 34.56% of the total size.



## Example

In the following example the `cnn.com` component's size (20.83% of the total size) may have contributed to the delay in its downloading. To reduce download time, it may help to reduce the size of this component.



# System Resource Graphs

## System Resource Graphs Overview

System Resource graphs display the system resource usage measured by the online monitors during the load test scenario run. These graphs require that you specify the resources you want to measure *before* running the scenario. For more information, refer to the section on online monitors in the Controller section.

## Server Resources Performance Counters

The following table describes the available counters:

Monitor	Measurements	Description
CPU Monitor	Utilization	Measures CPU utilization.
Disk Space Monitor	Disk space	Measures the amount (in MB) free disk space and the percentage of disk space used.
Memory Monitor	MB free	Measures the amount of free memory (in MB).
	Pages/sec	Measures the number of virtual memory pages that are moved between main memory and disk storage.
	Percent used	Measures the percentage of memory and paging file space used.
Services Monitor		Monitors processes locally or on remote systems. Can be used to verify that specific processes are running.

## Linux Resources Default Measurements

The following default measurements are available for Linux machines:

Measurement	Description
Average load	Average number of processes simultaneously in 'Ready' state during the last minute.
Collision rate	Collisions per second detected on the Ethernet.
Context switches rate	Number of switches between processes or threads, per second.
CPU utilization	Percent of time that the CPU is utilized.
Disk rate	Rate of disk transfers.

, continued

Measurement	Description
<b>Incoming packets error rate</b>	Errors per second while receiving Ethernet packets.
<b>Incoming packets rate</b>	Incoming Ethernet packets per second.
<b>Interrupt rate</b>	Number of device interrupts per second.
<b>Outgoing packets errors rate</b>	Errors per second while sending Ethernet packets.
<b>Outgoing packets rate</b>	Outgoing Ethernet packets per second.
<b>Page-in rate</b>	Number of pages read to physical memory, per second.
<b>Page-out rate</b>	Number of pages written to pagefile(s) and removed from physical memory, per second.
<b>Paging rate</b>	Number of pages read to physical memory or written to pagefile(s), per second.
<b>Swap-in rate</b>	The rate by which disk content is swapped into the machine's memory in Kbps.
<b>Swap-out rate</b>	The rate by which the machine's memory is being swapped out to disk in Kbps.
<b>System mode CPU utilization</b>	Percent of time that the CPU is utilized in system mode.
<b>User mode CPU utilization</b>	Percent of time that the CPU is utilized in user mode.

## Windows Resources Default Measurements

The following default measurements are available for Windows Resources:

Object	Measurement	Description
<b>System</b>	<b>% Total Processor Time</b>	The average percentage of time that all the processors on the system are busy executing non-idle threads. On a multi-processor system, if all processors are always busy, this is 100%, if all processors are 50% busy this is 50% and if 1/4 of the processors are 100% busy this is 25%. It can be viewed as the fraction of the time spent doing useful work. Each processor is assigned an Idle thread in the Idle process which consumes those unproductive processor cycles not used by any other threads.

, continued

Object	Measurement	Description
Processor	% Processor Time	The percentage of time that the processor is executing a non-idle thread. This counter was designed as a primary indicator of processor activity. It is calculated by measuring the time that the processor spends executing the thread of the idle process in each sample interval, and subtracting that value from 100%. (Each processor has an idle thread which consumes cycles when no other threads are ready to run.) It can be viewed as the percentage of the sample interval spent doing useful work. This counter displays the average percentage of busy time observed during the sample interval. It is calculated by monitoring the time the service was inactive, and then subtracting that value from 100%.
System	File Data Operations/sec	The rate at which the computer issues read and write operations to file system devices. This does not include File Control Operations.
System	Processor Queue Length	The instantaneous length of the processor queue in units of threads. This counter is always 0 unless you are also monitoring a thread counter. All processors use a single queue in which threads wait for processor cycles. This length does not include the threads that are currently executing. A sustained processor queue length greater than two generally indicates processor congestion. This is an instantaneous count, not an average over the time interval.
Memory	Page Faults/sec	This is a count of the page faults in the processor. A page fault occurs when a process refers to a virtual memory page that is not in its Working Set in the main memory. A page fault will not cause the page to be fetched from disk if that page is on the standby list (and hence already in main memory), or if it is in use by another process with which the page is shared.
PhysicalDisk	% Disk Time	The percentage of elapsed time that the selected disk drive is busy servicing read or write requests.
Memory	Pool Nonpaged Bytes	The number of bytes in the non-paged pool, a system memory area where space is acquired by operating system components as they accomplish their appointed tasks. Non-paged pool pages cannot be paged out to the paging file. They remain in main memory as long as they are allocated.

, continued

Object	Measurement	Description
Memory	Pages/sec	The number of pages read from the disk or written to the disk to resolve memory references to pages that were not in memory at the time of the reference. This is the sum of Pages Input/sec and Pages Output/sec. This counter includes paging traffic on behalf of the system cache to access file data for applications. This value also includes the pages to/from non-cached mapped memory files. This is the primary counter to observe if you are concerned about excessive memory pressure (that is, thrashing), and the excessive paging that may result.
System	Total Interrupts/sec	The rate at which the computer is receiving and servicing hardware interrupts. The devices that can generate interrupts are the system timer, the mouse, data communication lines, network interface cards, and other peripheral devices. This counter provides an indication of how busy these devices are on a computer-wide basis. See also <b>Processor:Interrupts/sec</b> .
Objects	Threads	The number of threads in the computer at the time of data collection. Notice that this is an instantaneous count, not an average over the time interval. A thread is the basic executable entity that can execute instructions in a processor.
Process	Private Bytes	The current number of bytes that the process has allocated that cannot be shared with other processes.


## Server Resources Graph

This graph shows the resources (CPU, disk space, memory, or services) used on remote Linux servers measured during the load test scenario.

Purpose	This graph helps you determine the impact of Vuser load on the various system resources.
X-axis	Elapsed time since the start of the run.
Y-axis	The usage of resources on the Linux server.
See also	<a href="#">"System Resource Graphs Overview" on page 1523</a> <a href="#">"Server Resources Performance Counters" on page 1523</a>

### Example

In the following example, Windows resource utilization is measured during the load test scenario. It is shown as a function of the elapsed scenario time.




## Host Resources Graph

This graph displays a summary of the System Resources usage for each Windows based Performance Center host (Controller and Load Generators). measured during the load test scenario.

Purpose	This graph helps you determine the impact of Vuser load on the various host resources.
X-axis	Elapsed time since the start of the run.
Y-axis	The usage of resources on the Windows hosts.
See also	<a href="#">"System Resource Graphs Overview" on page 1523</a>

### Example

In the following example, you can see a peak in the usage of Disk Time and Processor Time as the Memory Usage gets less towards the end of the load test.




## SiteScope Graph

This graph displays statistics about the resource usage on the SiteScope machine during the load test scenario run.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the SiteScope machine.
See also	<a href="#">"System Resource Graphs Overview" on page 1523</a>

### Example

In the following example, the percentage of memory resources used, the number of pages read per second, and the CPU utilization.




## SNMP Resources Graph

This graph shows statistics for machines running an SNMP agent, using the Simple Network Management Protocol (SNMP).

X-axis	Elapsed time since the start of the run.
Y-axis	The usage of resources on a machine running the SNMP agent.
Note	To obtain data for this graph, you need to enable the SNMP monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"System Resource Graphs Overview" on page 1523</a>

### Example

In the following example SNMP measurements are displayed for a machine called bonaporte.




## Linux Resources Graph

This graph shows the Linux resources measured during the load test scenario. The Linux measurements include those available by the **rstatd** daemon: average load, collision rate, context switch rate, CPU utilization, incoming packets error rate, incoming packets rate, interrupt rate, outgoing packets error rate, outgoing packets rate, page-in rate, page-out rate, paging rate, swap-in rate, swap-out rate, system mode CPU utilization, and user mode CPU utilization.

<b>Purpose</b>	This graph helps you determine the impact of Vuser load on the various system resources.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The usage of resources on the Linux machine.
<b>Note</b>	To obtain data for this graph, you need to select the desired measurements for the online monitor (from the Controller) before running the scenario.
<b>See also</b>	<a href="#">"Linux Resources Default Measurements" on page 1523</a>

### Example

In the following example Linux resources are measured during the load test scenario.




## Windows Resources Graph

This graph shows the Windows resources measured during the load test scenario. The Windows measurements correspond to the built-in counters available from the Windows Performance Monitor.

<b>Purpose</b>	This graph helps you determine the impact of Vuser load on the various system resources.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The usage of resources on the Windows machine running the load test scenario.
<b>Note</b>	To obtain data for this graph, you need to select the desired measurements for the online monitor (from the Controller) before running the scenario.
<b>See also</b>	<a href="#">"System Resource Graphs Overview" on page 1523</a> <a href="#">"Windows Resources Default Measurements" on page 1524</a>

### Example

In the following example Windows resources are measured on the server running the load test scenario.



## Network Virtualization Graphs

### Packet Loss Graph


This graph shows packets lost during the last second of the scenario run. Packet loss occurs when data packets fail to reach their destination. It can result from gateway overload, signal degradation, channel congestion, or faulty hardware.

<b>Purpose</b>	Helps you understand how many data packets were lost over a specific time interval.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The following measurements: <ul style="list-style-type: none"><li>The percentage of lost packets from all packets that were sent.</li><li>The number of data packets that were lost over 60 seconds.</li><li>The total number of packets that were lost.</li></ul>
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.

<b>Tip</b>	For LoadRunner Analysis (not applicable to monitoring graphs):  To view information for a specific location: <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<a href="#">"Network Virtualization Graphs" on the previous page</a>


### Example - Network Virtualization Per Group

The following example shows how the total of packet loss for the **USA** group increased as the scenario progressed.



### Example - Network Virtualization Per Load Generator

In the following example, you can see that the packet loss is grouped by load generator. This was the mode selected when you enabled Network Virtualization for the scenario.



### Average Latency Graph


This graph shows the average recorded time required for a packet of data to travel from the indicated source point to the required destination, measured in milliseconds in the last 60 seconds.

<b>Purpose</b>	Helps you evaluate the time required for a packet of data to travel over the network.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The average latency—the time in milliseconds required for a packet of data to reach its destination, per 60 second intervals.
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.

<b>Tips</b>	<p>For LoadRunner Analysis (not applicable to monitoring graphs):</p> <p>To view information for a specific location:</p> <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<ul style="list-style-type: none"><li>• <a href="#">"Network Virtualization Graphs" on page 1532</a></li><li>• <a href="#">"Custom Filter Dialog Box" on page 1404</a></li></ul>

### Example - Network Virtualization Per Group

In the following example, you can see that the latency for the **USA** group reached its peak at nearly 4 minutes into the scenario run, while the **Ukraine** group remained fairly constant at approximately 14 msec.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the ["Packet Loss Graph" on page 1532](#).


## Average Bandwidth Utilization Graph

This graph shows the average bandwidth utilized by a virtual user or a virtualized location from the maximal available bandwidth allocated for it during the last second, measured in percentages.

<b>Purpose</b>	Helps you evaluate the bandwidth used over your network.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The percentage of bandwidth utilization.
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>Tips</b>	<p>For LoadRunner Analysis (not applicable to monitoring graphs):</p> <p>To view information for a specific location:</p> <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<a href="#">"Network Virtualization Graphs" on page 1532</a>

### Example

In the following example, you can see that the bandwidth utilization for all locations and measurements, was constant at 10%.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the ["Packet Loss Graph" on page 1532](#).

## Average Throughput Graph


This graph shows the average data traffic passing to or from the virtualized location, measured in kilobytes per second (kbps).

<b>Purpose</b>	Helps you evaluate the amount of load Vusers generate, in terms of the number of server and client throughput. The graph shows metrics for input and output traffic for both the server and client machines. Use the legend below the graph to determine the line color for each metric.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The rate of data passing to and from the virtual location, in kbps for the following metrics per group or load generator: <ul style="list-style-type: none"><li>• Input to the client machine</li><li>• Output from the client machine</li><li>• Input to the server machine</li><li>• Output from the server machine</li></ul>

<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the General tab of the Options dialog box.
<b>Tips</b>	<p>For LoadRunner Analysis (not applicable to monitoring graphs):</p> <p>To view information for a specific location:</p> <ol style="list-style-type: none"> <li>1. Click within the graph.</li> <li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li> <li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li> </ol>
<b>See also</b>	<a href="#">"Total Throughput Graph" on the next page</a>

### Example

In the following example, the average server input throughput was the lowest for the **Ukraine** group.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the ["Packet Loss Graph" on page 1532](#).


## Total Throughput Graph

Displays the total data traffic passing to or from the virtualized location, measured in kilobytes.

<b>Purpose</b>	Helps you evaluate the total amount of load that Vusers generate while running a scenario with network virtualization.  The graph shows metrics for input and output traffic for both the server and client machines. The legend below the graph indicates the line color for each of these metrics.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Throughput of the server, in kilobytes per second (Kbps).
<b>Note</b>	You cannot change the granularity of the x-axis to a value that is less than the Web granularity you defined in the <b>General</b> tab of the Options dialog box.
<b>Tips</b>	For LoadRunner Analysis (not applicable to monitoring graphs):  To view information for a specific location: <ol style="list-style-type: none"><li>1. Click within the graph.</li><li>2. Select <b>Set Filter/ Sort By</b> from the right-click menu to open the Graph Settings dialog box.</li><li>3. In the <b>Filter condition</b> section, select the <i>Location Name</i> row, and select the desired location from the drop-down list.</li></ol>
<b>See also</b>	<a href="#">"Average Throughput Graph" on page 1537</a>

### Example

In the following example, the highest throughput level was for the input data to the client, for the **Ukraine** group.



If you enabled Network Virtualization per load generator (and not per group), the graph shows the measurements per load generator, as shown in the "["Packet Loss Graph" on page 1532](#)".

## Firewall Server Graphs

### Firewall Server Monitor Graphs Overview

Firewall server monitor graphs provide you with performance information for firewall servers. In order to obtain data for this graph, you need to activate the Firewall server online monitor before running the load test scenario. When you set up the online monitor for the Firewall server, you indicate which statistics and measurements to monitor. For more information on activating and configuring Firewall server monitors, refer to the *HP LoadRunner Controller User Guide*.

### Check Point FireWall-1 Server Measurements

The following measurements are available for the Check Point Firewall-1 server:

Measurement	Description
<b>fwRejected</b>	The number of rejected packets.
<b>fwDropped</b>	The number of dropped packets.
<b>fwLogged</b>	The number of logged packets.


## Check Point FireWall-1 Server Graph

This graph shows statistics on Check Point's Firewall server as a function of the elapsed load test scenario time.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the Check Point Firewall-1 server.
Note	To obtain data for this graph, you need to enable the Check Point FireWall-1 monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Firewall Server Monitor Graphs Overview" on the previous page</a> <a href="#">"Check Point FireWall-1 Server Measurements" on the previous page</a>

### Example

In the following example the graph displays the **fwDropped**, **fwLogged**, and **fwRejected** measurements during the first minute and twenty seconds of the scenario. There are differences in the scale factor for the measurements: the scale factor for **fwDropped** is 1, the scale factor for **fwLogged** is 10, and the scale factor for **fwRejected** is 0.0001.



## Web Server Resource Graphs

## Web Server Resource Graphs Overview

Web Server Resource graphs provide you with information about the resource usage of the Apache and Microsoft IIS Web servers. In order to obtain data for these graphs, you need to activate the online monitor for the server and specify which resources you want to measure before running the load test scenario. For information on activating and configuring the Web Server Resource monitors, refer to the *HP LoadRunner Controller User Guide*.

In order to display all the measurements on a single graph, Analysis may scale them. The Legend window indicates the scale factor for each resource. To obtain the true value, multiply the scale factor by the displayed value.

### Apache Server Measurements

The following default measurements are available for the Apache server:

Measurement	Description
# Busy Servers	The number of servers in the Busy state
# Idle Servers	The number of servers in the Idle state
Apache CPU Usage	The percentage of time the CPU is utilized by the Apache server
Hits/sec	The HTTP request rate
KBytes Sent/sec	The rate at which data bytes are sent from the Web server

### IIS Server Measurements

The following default measurements are available for the IIS server:

Object	Measurement	Description
Web Service	Bytes Sent/sec	The rate at which the data bytes are sent by the Web service.
Web Service	Bytes Received/sec	The rate at which the data bytes are received by the Web service.
Web Service	Get Requests/sec	The rate at which HTTP requests using the GET method are made. Get requests are generally used for basic file retrievals or image maps, though they can be used with forms.
Web Service	Post Requests/sec	The rate at which HTTP requests using the POST method are made. Post requests are generally used for forms or gateway requests.

, continued

Object	Measurement	Description
Web Service	Maximum Connections	The maximum number of simultaneous connections established with the Web service.
Web Service	Current Connections	The current number of connections established with the Web service.
Web Service	Current NonAnonymous Users	The number of users that currently have a non-anonymous connection using the Web service.
Web Service	Not Found Errors/sec	The rate of errors due to requests that could not be satisfied by the server because the requested document could not be found. These are generally reported to the client as an HTTP 404 error code.
Process	Private Bytes	The current number of bytes that the process has allocated that cannot be shared with other processes.

## Apache Server Graph


This graph shows server statistics as a function of the elapsed load test scenario time.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the Apache server during the scenario run.
Note	To obtain data for this graph, you need to enable the Apache online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Web Server Resource Graphs Overview"</a> on the previous page <a href="#">"Apache Server Measurements"</a> on the previous page

### Example

In the following example, the CPU usage remained steady throughout the scenario. At the end of the scenario, the number of idle servers increased. The number of busy servers remained steady at 1 throughout the scenario, implying that the Vuser only accessed one Apache server.

The scale factor for the **Busy Servers** measurement is 1/10 and the scale factor for **CPU usage** is 10.



## Microsoft Information Internet Server (IIS) Graph


This graph shows server statistics as a function of the elapsed load test scenario time.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the MS IIS.
Note	To obtain data for this graph, you need to enable the MS IIS online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Web Server Resource Graphs Overview" on page 1542</a> <a href="#">"IIS Server Measurements" on page 1542</a>

### Example

In the following example the **Bytes Received/sec** and **Get Requests/sec** measurements remained fairly steady throughout the scenario, while the **% Total Processor Time**, **Bytes Sent/sec**, and **Post Requests/sec** measurements fluctuated considerably.

The scale factor for the **Bytes Sent/sec** and **Bytes Received/sec** measurements is 1/100, and the scale factor for the **Post Requests/sec** measurement is 10.



## Web Application Server Resource Graphs

### ***Web Application Server Resource Graphs Overview***

Web Application Server Resource graphs provide you with resource usage information about the Ariba, ATG Dynamo, BroadVision, ColdFusion, Fujitsu INTERSTAGE, iPlanet (NAS), Microsoft ASP, Oracle9iAS HTTP, SilverStream, WebLogic (SNMP), WebLogic (JMX), and WebSphere application servers.

In order to obtain data for these graphs, you need to activate the online monitor for the application server and specify which resources you want to measure before running the load test scenario. For information on activating and configuring the Web Application Server Resource monitors, refer to the *HP LoadRunner Controller User Guide*.

When you open a Web Application Server Resource graph, you can filter it to show only the relevant application. When you need to analyze other applications, you can change the filter conditions and display the desired resources.

In order to display all the measurements on a single graph, Analysis may scale them. The Legend window indicates the scale factor for each resource. To obtain the true value, multiply the scale factor by the displayed value. For more information on scaled measurements, see the example in "Web Server Resource Graphs Overview" on page 1542.

## **Web Application Server Resource Graphs Measurements**

### **Microsoft Active Server Pages (ASP) Measurements**

The following default measurements are available for Microsoft Active Server Pages:

>Measurement	Description
<b>Errors per Second</b>	The number of errors per second.
<b>Requests Wait Time</b>	The number of milliseconds the most recent request was waiting in the queue.
<b>Requests Executing</b>	The number of requests currently executing.
<b>Requests Queued</b>	The number of requests waiting in the queue for service.
<b>Requests Rejected</b>	The total number of requests not executed because there were insufficient resources to process them.
<b>Requests Not Found</b>	The number of requests for files that were not found.
<b>Requests/sec</b>	The number of requests executed per second.
<b>Memory Allocated</b>	The total amount of memory (in bytes) currently allocated by Active Server Pages.
<b>Errors During Script Run-Time</b>	The number of failed requests due to run time errors.
<b>Sessions Current</b>	The current number of sessions being serviced.
<b>Transactions/sec</b>	The number of transactions started per second.

### **Oracle9iAS HTTP Server Modules**

The following table describes some of the modules that are available for the Oracle9iAS HTTP server:

Measurement	Description
<b>mod_mime.c</b>	Determines document types using file extensions.
<b>mod_mime_magic.c</b>	Determines document types using "magic numbers".
<b>mod_auth_anon.c</b>	Provides anonymous user access to authenticated areas.
<b>mod_auth_dbm.c</b>	Provides user authentication using DBM files.

, continued

Measurement	Description
<b>mod_auth_digest.c</b>	Provides MD5 authentication.
<b>mod_cern_meta.c</b>	Supports HTTP header metafiles.
<b>mod_digest.c</b>	Provides MD5 authentication (deprecated by mod_auth_digest).
<b>mod_expires.c</b>	Applies Expires: headers to resources.
<b>mod_headers.c</b>	Adds arbitrary HTTP headers to resources.
<b>mod_proxy.c</b>	Provides caching proxy abilities.
<b>mod_rewrite.c</b>	Provides powerful URI-to-filename mapping using regular expressions.
<b>mod_speling.c</b>	Automatically corrects minor typos in URLs.
<b>mod_info.c</b>	Provides server configuration information.
<b>mod_status.c</b>	Displays server status.
<b>mod_usertrack.c</b>	Provides user tracking using cookies.
<b>mod_dms.c</b>	Provides access to DMS Apache statistics.
<b>mod_perl.c</b>	Allows execution of Perl scripts.
<b>mod_fastcgi.c</b>	Supports CGI access to long-lived programs.
<b>mod_ssl.c</b>	Provides SSL support.
<b>mod_plsql.c</b>	Handles requests for Oracle stored procedures.
<b>mod_isapi.c</b>	Provides Windows ISAPI extension support.
<b>mod_setenvif.c</b>	Sets environment variables based on client information.
<b>mod_actions.c</b>	Executes CGI scripts based on media type or request method.

, continued

Measurement	Description
<b>mod_imap.c</b>	Handles imagemap files.
<b>mod_asis.c</b>	Sends files that contain their own HTTP headers.
<b>mod_log_config.c</b>	Provides user-configurable logging replacement for mod_log_common.
<b>mod_env.c</b>	Passes environments to CGI scripts.
<b>mod_alias.c</b>	Maps different parts of the host file system in the document tree, and redirects URLs.
<b>mod_userdir.c</b>	Handles user home directories.
<b>mod_cgi.c</b>	Invokes CGI scripts.
<b>mod_dir.c</b>	Handles the basic directory.
<b>mod_autoindex.c</b>	Provides automatic directory listings.
<b>mod_include.c</b>	Provides server-parsed documents.
<b>mod_negotiation.c</b>	Handles content negotiation.
<b>mod_auth.c</b>	Provides user authentication using text files.
<b>mod_access.c</b>	Provides access control based on the client host name or IP address.
<b>mod_so.c</b>	Supports loading modules (.so on UNIX, .dll on Win32) at run time.
<b>mod_oprocmgr.c</b>	Monitors JServ processes and restarts them if they fail.
<b>mod_jserv.c</b>	Routes HTTP requests to JServ server processes. Balances load across multiple JServs by distributing new requests in round-robin order.
<b>mod_ose.c</b>	Routes requests to the JVM embedded in Oracle's database server.
<b>http_core.c</b>	Handles requests for static Web pages.

## Oracle9iAS HTTP Server Counters

The following table describes the counters that are available for the Oracle9iAS HTTP server:

Measurement	Description
<b>handle.minTime</b>	The minimum time spent in the module handler.
<b>handle.avg</b>	The average time spent in the module handler.
<b>handle.active</b>	The number of threads currently in the handle processing phase.
<b>handle.time</b>	The total amount of time spent in the module handler.
<b>handle.completed</b>	The number of times the handle processing phase was completed.
<b>request.maxTime</b>	The maximum amount of time required to service an HTTP request.
<b>request.minTime</b>	The minimum amount of time required to service an HTTP request.
<b>request.avg</b>	The average amount of time required to service an HTTP request.
<b>request.active</b>	The number of threads currently in the request processing phase.
<b>request.time</b>	The total amount of time required to service an HTTP request.
<b>request.completed</b>	The number of times the request processing phase was completed.
<b>connection.maxTime</b>	The maximum amount of time spent servicing any HTTP connection.
<b>connection.minTime</b>	The minimum amount of time spent servicing any HTTP connection.
<b>connection.avg</b>	The average amount of time spent servicing HTTP connections.
<b>connection.active</b>	The number of connections with currently open threads.
<b>connection.time</b>	The total amount of time spent servicing HTTP connections.
<b>connection.completed</b>	The number of times the connection processing phase was completed.
<b>numMods.value</b>	The number of loaded modules.
<b>childFinish.count</b>	The number of times the Apache parent server started a child server, for any reason.
<b>childStart.count</b>	The number of times "children"finished "gracefully."There are some ungraceful error/crash cases that are not counted in childFinish.count.
<b>Decline.count</b>	The number of times each module declined HTTP requests.
<b>internalRedirect.count</b>	The number of times that any module passed control to another module using an "internal redirect".
<b>cpuTime.value</b>	The total CPU time utilized by all processes on the Apache server (measured in CPU milliseconds).
<b>heapSize.value</b>	The total heap memory utilized by all processes on the Apache server (measured in kilobytes).

, continued

Measurement	Description
<b>pid.value</b>	The process identifier of the parent Apache process.
<b>upTime.value</b>	The amount of time the server has been running (measured in milliseconds).

## WebLogic (SNMP) Server Table Measurements

The Server Table lists all WebLogic (SNMP) servers that are being monitored by the agent. A server must be contacted or be reported as a member of a cluster at least once before it will appear in this table. Servers are only reported as a member of a cluster when they are actively participating in the cluster, or shortly thereafter.

Measurement	Description
<b>ServerState</b>	The state of the WebLogic server, as inferred by the SNMP agent. <b>Up</b> implies that the agent can contact the server. <b>Down</b> implies that the agent cannot contact the server.
<b>ServerLoginEnable</b>	<b>True</b> if client logins are enabled on the server.
<b>ServerMaxHeapSpace</b>	The maximum heap size for this server (in KB).
<b>ServerHeapUsedPct</b>	The percentage of heap space currently in use on the server.
<b>ServerQueueLength</b>	The current length of the server execute queue.
<b>ServerQueueThroughput</b>	The current throughput of execute queue, expressed as the number of requests processed per second.
<b>ServerNumEJBDeployment</b>	The total number of EJB deployment units known to the server.
<b>ServerNumEJBBeansDeployed</b>	The total number of EJB beans actively deployed on the server.

## WebLogic (SNMP) Listen Table Measurements

The Listen Table is the set of protocol, IP address, and port combinations on which servers are listening. There will be multiple entries for each server: one for each (protocol, ipAddr, port) combination. If clustering is used, the clustering-related MIB objects will assume a higher priority.

Measurement	Description
<b>ListenPort</b>	Port number.
<b>ListenAdminOK</b>	<b>True</b> if admin requests are allowed on this (protocol, ipAddr, port) combination; otherwise false.

, continued

Measurement	Description
ListenState	<b>Listening</b> if the (protocol, ipAddr, port) combination is enabled on the server; <b>Not Listening</b> if it is not. The server may be listening but not accepting new clients if its server Login Enable state is false. In this case, existing clients will continue to function, but new ones will not.

### WebLogic (SNMP) ClassPath Table Measurements

The ClassPath Table is the table of classpath elements for Java, WebLogic (SNMP) server, and servlets. There are multiple entries in this table for each server. There may also be multiple entries for each path on a server. If clustering is used, the clustering-related MIB objects will assume a higher priority.

Measurement	Description
CPType	The type of CP element: Java, WebLogic, servlet. A Java CPType means the CP element is one of the elements in the normal Java classpath. A WebLogic CPType means the CP element is one of the elements in weblogic.class.path. A servlet CPType means the CP element is one of the elements in the dynamic servlet classpath.
CPIndex	The position of an element within its path. The index starts at 1.

### Websphere Application Server Monitor Run-Time Resource Measurements

Contains resources related to the Java Virtual Machine run time, as well as the ORB.

Measurement	Description
MemoryFree	The amount of free memory remaining in the Java Virtual Machine.
MemoryTotal	The total memory allocated for the Java Virtual Machine.
MemoryUse	The total memory in use on the Java Virtual Machine.

### Websphere Application Server Monitor BeanData Measurements

Every home on the server provides performance data, depending on the type of bean deployed in the home. The top level bean data holds an aggregate of all the containers.

Measurement	Description
BeanDestroys	The number of times an individual bean object was destroyed. This applies to any bean, regardless of its type.
StatelessBeanDestroys	The number of times a stateless session bean object was destroyed.
StatefulBeanDestroys	The number of times a stateful session bean object was destroyed.

## Websphere Application Server Monitor BeanObjectPool Measurements

The server holds a cache of bean objects. Each home has a cache and there is therefore one BeanObjectPoolContainer per container. The top level, BeanObjectPool, holds an aggregate of all the containers data.

Measurement	Description
<b>NumGetFound</b>	The number of calls to the pool that resulted in finding an available bean.
<b>NumPutsDiscarded</b>	The number of times releasing a bean to the pool resulted in the bean being discarded because the pool was full.

## Websphere Application Server Monitor OrbThreadPool Measurements

These are resources related to the ORB thread pool that is on the server.

Measurement	Description
<b>ActiveThreads</b>	The average number of active threads in the pool.
<b>TotalThreads</b>	The average number of threads in the pool.
<b>PercentTimeMaxed</b>	The average percent of the time that the number of threads in the pool reached or exceeded the desired maximum number.

## Websphere Application Server Monitor DBConnectionMgr Measurements

These are resources related to the database connection manager. The manager consists of a series of data sources, as well as a top-level aggregate of each of the performance metrics.

Measurement	Description
<b>ConnectionWaitTime</b>	The average time (in seconds) of a connection grant.
<b>ConnectionTime</b>	The average time (in seconds) that a connection is in use.
<b>ConnectionPercentUsed</b>	The average percentage of the pool that is in use.

## Websphere Application Server Monitor TransactionData Measurements

These are resources that pertain to transactions.

Measurement	Description
<b>NumTransactions</b>	The number of transactions processed.
<b>ActiveTransactions</b>	The average number of active transactions.
<b>TransactionRT</b>	The average duration of each transaction.
<b>RolledBack</b>	The number of transactions rolled back.
<b>Timeouts</b>	The number of transactions that timed out due to inactivity timeouts.
<b>TransactionSuspended</b>	The average number of times that a transaction was suspended.

## Websphere Application Server Monitor ServletEngine Measurements

These are resources that are related to servlets and JSPs.

Measurement	Description
ServletErrors	The number of requests that resulted in an error or an exception.

## Websphere Application Server Monitor Session Measurements

These are general metrics regarding the HTTP session pool.

Measurement	Description
SessionsInvalidated	The number of invalidated sessions. May not be valid when using sessions in the database mode.

## Microsoft Active Server Pages (ASP) Graph

This graph displays statistics about the resource usage on the ASP server during the load test scenario run.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the ASP server.
Note	To obtain data for this graph, you need to enable the Microsoft ASP online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Web Application Server Resource Graphs Overview" on page 1545</a> <a href="#">"Web Application Server Resource Graphs Measurements" on page 1546</a>

## Oracle9iAS HTTP Server Graph

This graph displays statistics about the resource usage on the Oracle9iAS HTTP server during the load test scenario run.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the Oracle9iAS HTTP server.
Note	To obtain data for this graph, you need to enable the Oracle9iAS HTTP online monitor (from the Controller), and select the default measurements you want to display, before running the scenario.

**See also**

["Web Application Server Resource Graphs Overview" on page 1545](#)  
["Web Application Server Resource Graphs Measurements" on page 1546](#)

## **WebLogic (SNMP) Graph**

This graph displays statistics about the resource usage on the WebLogic (SNMP) server (version 6.0 and earlier) during the load test scenario run.

<b>X-axis</b>	The elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the WebLogic (SNMP) server.
<b>Note</b>	To obtain data for this graph, you need to enable the WebLogic (SNMP) online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"Web Application Server Resource Graphs Overview" on page 1545</a> <a href="#">"Web Application Server Resource Graphs Measurements" on page 1546</a>

## **WebSphere Application Server Graph**

This graph displays statistics about the resource usage on the WebSphere application server during the load test scenario run.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the WebSphere Application server.
<b>Note</b>	To obtain data for this graph, you need to configure the WebSphere Application Server online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"Web Application Server Resource Graphs Overview" on page 1545</a> <a href="#">"Web Application Server Resource Graphs Measurements" on page 1546</a>

## **Database Server Resource Graphs**

### **Database Server Resource Graphs Overview**

The Database Server Resource graphs show statistics for several database servers. Currently DB2, Oracle, SQL server, and Sybase databases are supported. These graphs require that you

specify the resources you want to measure *before* running the load test scenario. For more information, refer to the section on online monitors in the *HP LoadRunner Controller User Guide*.

## DB2 Database Manager Counters

Measurement	Description
<b>rem_cons_in</b>	The current number of connections initiated from remote clients to the instance of the database manager that is being monitored.
<b>rem_cons_in_exec</b>	The number of remote applications that are currently connected to a database and are currently processing a unit of work within the database manager instance being monitored.
<b>local_cons</b>	The number of local applications that are currently connected to a database within the database manager instance being monitored.
<b>local_cons_in_exec</b>	The number of local applications that are currently connected to a database within the database manager instance being monitored and are currently processing a unit of work.
<b>con_local_dbases</b>	The number of local databases that have applications connected.
<b>agents_registered</b>	The number of agents registered in the database manager instance that is being monitored (coordinator agents and subagents).
<b>agents_waiting_on_token</b>	The number of agents waiting for a token so they can execute a transaction in the database manager.
<b>idle_agents</b>	The number of agents in the agent pool that are currently unassigned to an application and are therefore "idle".
<b>agents_from_pool</b>	The number of agents assigned from the agent pool.
<b>agents_created_empty_pool</b>	The number of agents created because the agent pool was empty.
<b>agents_stolen</b>	The number of times that agents are stolen from an application. Agents are stolen when an idle agent associated with an application is reassigned to work on a different application.
<b>comm_private_mem</b>	The amount of private memory that the instance of the database manager has currently committed at the time of the snapshot.
<b>inactive_gw_agents</b>	The number of DRDA agents in the DRDA connections pool that are primed with a connection to a DRDA database, but are inactive.

, continued

Measurement	Description
<b>num_gw_conn_switches</b>	The number of times that an agent from the agents pool was primed with a connection and was stolen for use with a different DRDA database.
<b>sort_heap_allocated</b>	The total number of allocated pages of sort heap space for all sorts at the level chosen and at the time the snapshot was taken.
<b>post_threshold_sorts</b>	The number of sorts that have requested heaps after the sort heap threshold has been reached.
<b>piped_sorts_requested</b>	The number of piped sorts that have been requested.
<b>piped_sorts_accepted</b>	The number of piped sorts that have been accepted.

## DB2 Database Counters

Measurement	Description
<b>appls_cur_cons</b>	Indicates the number of applications that are currently connected to the database.
<b>appls_in_db2</b>	Indicates the number of applications that are currently connected to the database, and for which the database manager is currently processing a request.
<b>total_sec_cons</b>	The number of connections made by a sub-agent to the database at the node.
<b>num_assoc_agents</b>	At the application level, this is the number of sub-agents associated with an application. At the database level, it is the number of sub-agents for all applications.
<b>sort_heap_allocated</b>	The total number of allocated pages of sort heap space for all sorts at the level chosen and at the time the snapshot was taken.
<b>total_sorts</b>	The total number of sorts that have been executed.
<b>total_sort_time</b>	The total elapsed time (in milliseconds) for all sorts that have been executed.
<b>sort_overflows</b>	The total number of sorts that ran out of sort heap and may have required disk space for temporary storage.
<b>active_sorts</b>	The number of sorts in the database that currently have a sort heap allocated.

, continued

<b>Measurement</b>	<b>Description</b>
<b>total_hash_joins</b>	The total number of hash joins executed.
<b>total_hash_loops</b>	The total number of times that a single partition of a hash join was larger than the available sort heap space.
<b>hash_join_overflows</b>	The number of times that hash join data exceeded the available sort heap space.
<b>hash_join_small_overflows</b>	The number of times that hash join data exceeded the available sort heap space by less than 10%.
<b>pool_data_l_reads</b>	The number of logical read requests for data pages that have gone through the buffer pool.
<b>pool_data_p_reads</b>	The number of read requests that required I/O to get data pages into the buffer pool.
<b>pool_data_writes</b>	Indicates the number of times a buffer pool data page was physically written to disk.
<b>pool_index_l_reads</b>	The number of logical read requests for index pages that have gone through the buffer pool.
<b>pool_index_p_reads</b>	The number of physical read requests to get index pages into the buffer pool.
<b>pool_index_writes</b>	The number of times a buffer pool index page was physically written to disk.
<b>pool_read_time</b>	The total amount of elapsed time spent processing read requests that caused data or index pages to be physically read from disk to buffer pool.
<b>pool_write_time</b>	The total amount of time spent physically writing data or index pages from the buffer pool to disk.
<b>files_closed</b>	The total number of database files closed.
<b>pool_async_data_reads</b>	The number of pages read asynchronously into the buffer pool.
<b>pool_async_dataWrites</b>	The number of times a buffer pool data page was physically written to disk by either an asynchronous page cleaner, or a pre-fetcher. A pre-fetcher may have written dirty pages to disk to make space for the pages being pre-fetched.
<b>pool_async_indexWrites</b>	The number of times a buffer pool index page was physically written to disk by either an asynchronous page cleaner, or a pre-fetcher. A pre-fetcher may have written dirty pages to disk to make space for the pages being pre-fetched.

, continued

Measurement	Description
<b>pool_async_index_reads</b>	The number of index pages read asynchronously into the buffer pool by a pre-fetcher.
<b>pool_async_read_time</b>	The total elapsed time spent reading by database manager pre-fetchers.
<b>pool_async_write_time</b>	The total elapsed time spent writing data or index pages from the buffer pool to disk by database manager page cleaners.
<b>pool_async_data_read_reqs</b>	The number of asynchronous read requests.
<b>pool_lsn_gap_clns</b>	The number of times a page cleaner was invoked because the logging space used had reached a pre-defined criterion for the database.
<b>pool_drtv_pg_stal_clns</b>	The number of times a page cleaner was invoked because a synchronous write was needed during the victim buffer replacement for the database.
<b>pool_drtv_pg_thrsh_clns</b>	The number of times a page cleaner was invoked because a buffer pool had reached the dirty page threshold criterion for the database.
<b>prefetch_wait_time</b>	The time an application spent waiting for an I/O server (pre-fetcher) to finish loading pages into the buffer pool.
<b>pool_data_to_estore</b>	The number of buffer pool data pages copied to extended storage.
<b>pool_index_to_estore</b>	The number of buffer pool index pages copied to extended storage.
<b>pool_data_from_estore</b>	The number of buffer pool data pages copied from extended storage.
<b>pool_index_from_estore</b>	The number of buffer pool index pages copied from extended storage.
<b>direct_reads</b>	The number of read operations that do not use the buffer pool.
<b>direct_writes</b>	The number of write operations that do not use the buffer pool.
<b>direct_read_reqs</b>	The number of requests to perform a direct read of one or more sectors of data.
<b>direct_write_reqs</b>	The number of requests to perform a direct write of one or more sectors of data.

, continued

<b>Measurement</b>	<b>Description</b>
<b>direct_read_time</b>	The elapsed time (in milliseconds) required to perform the direct reads.
<b>direct_write_time</b>	The elapsed time (in milliseconds) required to perform the direct writes.
<b>cat_cache_lookups</b>	The number of times that the catalog cache was referenced to obtain table descriptor information.
<b>cat_cache_inserts</b>	The number of times that the system tried to insert table descriptor information into the catalog cache.
<b>cat_cache_overflows</b>	The number of times that an insert into the catalog cache failed due to the catalog cache being full.
<b>cat_cache_heap_full</b>	The number of times that an insert into the catalog cache failed due to a heap-full condition in the database heap.
<b>pkg_cache_lookups</b>	The number of times that an application looked for a section or package in the package cache. At a database level, it indicates the overall number of references since the database was started, or monitor data was reset.
<b>pkg_cache_inserts</b>	The total number of times that a requested section was not available for use and had to be loaded into the package cache. This count includes any implicit prepares performed by the system.
<b>pkg_cache_num_overflows</b>	The number of times that the package cache overflowed the bounds of its allocated memory.
<b>appl_section_lookups</b>	Lookups of SQL sections by an application from its SQL work area.
<b>appl_section_inserts</b>	Inserts of SQL sections by an application from its SQL work area.
<b>sec_logs_allocated</b>	The total number of secondary log files that are currently being used for the database.
<b>log_reads</b>	The number of log pages read from disk by the logger.
<b>log_writes</b>	The number of log pages written to disk by the logger.
<b>total_log_used</b>	The total amount of active log space currently used (in bytes) in the database.
<b>locks_held</b>	The number of locks currently held.

, continued

Measurement	Description
<b>lock_list_in_use</b>	The total amount of lock list memory (in bytes) that is in use.
<b>deadlocks</b>	The total number of deadlocks that have occurred.
<b>lock_escals</b>	The number of times that locks have been escalated from several row locks to a table lock.
<b>x_lock_escals</b>	The number of times that locks have been escalated from several row locks to one exclusive table lock, or the number of times an exclusive lock on a row caused the table lock to become an exclusive lock.
<b>lock_timeouts</b>	The number of times that a request to lock an object timed-out instead of being granted.
<b>lock_waits</b>	The total number of times that applications or connections waited for locks.
<b>lock_wait_time</b>	The total elapsed time waited for a lock.
<b>locks_waiting</b>	The number of agents waiting on a lock.
<b>rows_deleted</b>	The number of row deletions attempted.
<b>rows_inserted</b>	The number of row insertions attempted.
<b>rows_updated</b>	The number of row updates attempted.
<b>rows_selected</b>	The number of rows that have been selected and returned to the application.
<b>int_rows_deleted</b>	The number of rows deleted from the database as a result of internal activity.
<b>int_rows_updated</b>	The number of rows updated from the database as a result of internal activity.
<b>int_rows_inserted</b>	The number of rows inserted into the database as a result of internal activity caused by triggers.
<b>static_sql_stmts</b>	The number of static SQL statements that were attempted.
<b>dynamic_sql_stmts</b>	The number of dynamic SQL statements that were attempted.

, continued

<b>Measurement</b>	<b>Description</b>
<b>failed_sql_stmts</b>	The number of SQL statements that were attempted, but failed.
<b>commit_sql_stmts</b>	The total number of SQL COMMIT statements that have been attempted.
<b>rollback_sql_stmts</b>	The total number of SQL ROLLBACK statements that have been attempted.
<b>select_sql_stmts</b>	The number of SQL SELECT statements that were executed.
<b>uid_sql_stmts</b>	The number of SQL UPDATE, INSERT, and DELETE statements that were executed.
<b>ddl_sql_stmts</b>	The number of SQL Data Definition Language (DDL) statements that were executed.
<b>int_auto_rebinds</b>	The number of automatic rebinds (or recompiles) that have been attempted.
<b>int_commits</b>	The total number of commits initiated internally by the database manager.
<b>int_rollbacks</b>	The total number of rollbacks initiated internally by the database manager.
<b>int_deadlock_rollbacks</b>	The total number of forced rollbacks initiated by the database manager due to a deadlock. A rollback is performed on the current unit of work in an application selected by the database manager to resolve the deadlock.
<b>binds_precompiles</b>	The number of binds and pre-compiles attempted.

## ***DB2 Application Counters***

<b>Measurement</b>	<b>Description</b>
<b>agents_stolen</b>	The number of times that agents are stolen from an application. Agents are stolen when an idle agent associated with an application is reassigned to work on a different application.
<b>num_assoc_agents</b>	At the application level, this is the number of sub-agents associated with an application. At the database level, it is the number of sub-agents for all applications.
<b>total_sorts</b>	The total number of sorts that have been executed.

, continued

Measurement	Description
<b>total_sort_time</b>	The total elapsed time (in milliseconds) for all sorts that have been executed.
<b>sort_overflows</b>	The total number of sorts that ran out of sort heap and may have required disk space for temporary storage.
<b>total_hash_joins</b>	The total number of hash joins executed.
<b>total_hash_loops</b>	The total number of times that a single partition of a hash join was larger than the available sort heap space.
<b>hash_join_overflows</b>	The number of times that hash join data exceeded the available sort heap space
<b>hash_join_small_overflows</b>	The number of times that hash join data exceeded the available sort heap space by less than 10%.
<b>pool_data_l_reads</b>	The number of logical read requests for data pages that have gone through the buffer pool.
<b>pool_data_p_reads</b>	The number of read requests that required I/O to get data pages into the buffer pool.
<b>pool_data_writes</b>	The number of times a buffer pool data page was physically written to disk.
<b>pool_index_l_reads</b>	The number of logical read requests for index pages that have gone through the buffer pool.
<b>pool_index_p_reads</b>	The number of physical read requests to get index pages into the buffer pool.
<b>pool_index_writes</b>	The number of times a buffer pool index page was physically written to disk.
<b>pool_read_time</b>	The total amount of elapsed time spent processing read requests that caused data or index pages to be physically read from disk to buffer pool.
<b>prefetch_wait_time</b>	The time an application spent waiting for an I/O server (pre-fetcher) to finish loading pages into the buffer pool.
<b>pool_data_to_estore</b>	The number of buffer pool data pages copied to extended storage.
<b>pool_index_to_estore</b>	The number of buffer pool index pages copied to extended storage.

, continued

<b>Measurement</b>	<b>Description</b>
<b>pool_data_from_estore</b>	The number of buffer pool data pages copied from extended storage.
<b>pool_index_from_estore</b>	The number of buffer pool index pages copied from extended storage.
<b>direct_reads</b>	The number of read operations that do not use the buffer pool.
<b>direct_writes</b>	The number of write operations that do not use the buffer pool.
<b>direct_read_reqs</b>	The number of requests to perform a direct read of one or more sectors of data.
<b>direct_write_reqs</b>	The number of requests to perform a direct write of one or more sectors of data.
<b>direct_read_time</b>	The elapsed time (in milliseconds) required to perform the direct reads.
<b>direct_write_time</b>	The elapsed time (in milliseconds) required to perform the direct writes.
<b>cat_cache_lookups</b>	The number of times that the catalog cache was referenced to obtain table descriptor information.
<b>cat_cache_inserts</b>	The number of times that the system tried to insert table descriptor information into the catalog cache.
<b>cat_cache_overflows</b>	The number of times that an insert into the catalog cache failed due to the catalog cache being full.
<b>cat_cache_heap_full</b>	The number of times that an insert into the catalog cache failed due to a heap-full condition in the database heap.
<b>pkg_cache_lookups</b>	The number of times that an application looked for a section or package in the package cache. At a database level, it indicates the overall number of references since the database was started, or monitor data was reset.
<b>pkg_cache_inserts</b>	The total number of times that a requested section was not available for use and had to be loaded into the package cache. This count includes any implicit prepares performed by the system.
<b>appl_section_lookups</b>	Lookups of SQL sections by an application from its SQL work area.
<b>appl_section_inserts</b>	Inserts of SQL sections by an application from its SQL work area.

, continued

<b>Measurement</b>	<b>Description</b>
<b>uow_log_space_used</b>	The amount of log space (in bytes) used in the current unit of work of the monitored application.
<b>locks_held</b>	The number of locks currently held.
<b>deadlocks</b>	The total number of deadlocks that have occurred.
<b>lock_escals</b>	The number of times that locks have been escalated from several row locks to a table lock.
<b>x_lock_escals</b>	The number of times that locks have been escalated from several row locks to one exclusive table lock, or the number of times an exclusive lock on a row caused the table lock to become an exclusive lock.
<b>lock_timeouts</b>	The number of times that a request to lock an object timed-out instead of being granted.
<b>lock_waits</b>	The total number of times that applications or connections waited for locks.
<b>lock_wait_time</b>	The total elapsed time waited for a lock.
<b>locks_waiting</b>	The number of agents waiting on a lock.
<b>uow_lock_wait_time</b>	The total amount of elapsed time this unit of work has spent waiting for locks.
<b>rows_deleted</b>	The number of row deletions attempted.
<b>rows_inserted</b>	The number of row insertions attempted.
<b>rows_updated</b>	The number of row updates attempted.
<b>rows_selected</b>	The number of rows that have been selected and returned to the application.
<b>rows_written</b>	The number of rows changed (inserted, deleted or updated) in the table.
<b>rows_read</b>	The number of rows read from the table.
<b>int_rows_deleted</b>	The number of rows deleted from the database as a result of internal activity.
<b>int_rows_updated</b>	The number of rows updated from the database as a result of internal activity.

, continued

<b>Measurement</b>	<b>Description</b>
<b>int_rows_inserted</b>	The number of rows inserted into the database as a result of internal activity caused by triggers.
<b>open_rem_curs</b>	The number of remote cursors currently open for this application, including those cursors counted by `open_rem_curs_blk`.
<b>open_rem_curs_blk</b>	The number of remote blocking cursors currently open for this application.
<b>rej_curs_blk</b>	The number of times that a request for an I/O block at server was rejected and the request was converted to non-blocked I/O.
<b>acc_curs_blk</b>	The number of times that a request for an I/O block was accepted.
<b>open_loc_curs</b>	The number of local cursors currently open for this application, including those cursors counted by `open_loc_curs_blk`.
<b>open_loc_curs_blk</b>	The number of local blocking cursors currently open for this application.
<b>static_sql_stmts</b>	The number of static SQL statements that were attempted.
<b>dynamic_sql_stmts</b>	The number of dynamic SQL statements that were attempted.
<b>failed_sql_stmts</b>	The number of SQL statements that were attempted, but failed.
<b>commit_sql_stmts</b>	The total number of SQL COMMIT statements that have been attempted.
<b>rollback_sql_stmts</b>	The total number of SQL ROLLBACK statements that have been attempted.
<b>select_sql_stmts</b>	The number of SQL SELECT statements that were executed.
<b>uid_sql_stmts</b>	The number of SQL UPDATE, INSERT, and DELETE statements that were executed.
<b>ddl_sql_stmts</b>	This element indicates the number of SQL Data Definition Language (DDL) statements that were executed.
<b>int_auto_rebinds</b>	The number of automatic rebinds (or recompiles) that have been attempted.
<b>int_commits</b>	The total number of commits initiated internally by the database manager.

, continued

Measurement	Description
<b>int_rollbacks</b>	The total number of rollbacks initiated internally by the database manager.
<b>int_deadlock_rollbacks</b>	The total number of forced rollbacks initiated by the database manager due to a deadlock. A rollback is performed on the current unit of work in an application selected by the database manager to resolve the deadlock.
<b>binds_precompiles</b>	The number of binds and pre-compiles attempted.

## Oracle Server Monitoring Measurements

The following measurements are most commonly used when monitoring the Oracle server (from the V\$SYSSTAT table):

Measurement	Description
<b>CPU used by this session</b>	The amount of CPU time (in tens of milliseconds) used by a session between the time a user call started and ended. Some user calls can be completed within 10 milliseconds and, as a result, the start- and end-user call time can be the same. In this case, 0 milliseconds are added to the statistic. A similar problem can exist in the operating system reporting, especially on systems that suffer from many context switches.
<b>Bytes received via SQL*Net from client</b>	The total number of bytes received from the client over Net8.
<b>Logons current</b>	The total number of current logons.
<b>Opens of replaced files</b>	The total number of files that needed to be reopened because they were no longer in the process file cache.
<b>User calls</b>	Oracle allocates resources (Call State Objects) to keep track of relevant user call data structures every time you log in, parse, or execute. When determining activity, the ratio of user calls to RPI calls gives you an indication of how much internal work is generated as a result of the type of requests the user is sending to Oracle.
<b>SQL*Net roundtrips to/from client</b>	The total number of Net8 messages sent to, and received from, the client.

, continued

Measurement	Description
<b>Bytes sent via SQL*Net to client</b>	The total number of bytes sent to the client from the foreground process(es).
<b>Opened cursors current</b>	The total number of current open cursors.
<b>DB block changes</b>	Closely related to consistent changes, this statistic counts the total number of changes that were made to all blocks in the SGA that were part of an update or delete operation. These are changes that generate redo log entries and hence cause permanent changes to the database if the transaction is committed. This statistic is a rough indication of total database work and indicates (possibly on a per-transaction level) the rate at which buffers are being dirtied.
<b>Total file opens</b>	The total number of file opens being performed by the instance. Each process needs a number of files (control file, log file, database file) in order to work against the database.

## SQL Server Default Counters

Measurement	Description
<b>% Total Processor Time</b>	The average percentage of time that all the processors on the system are busy executing non-idle threads. On a multi-processor system, if all processors are always busy, this is 100%, if all processors are 50% busy this is 50% and if 1/4 of the processors are 100% busy this is 25%. It can be viewed as the fraction of the time spent doing useful work. Each processor is assigned an Idle thread in the Idle process which consumes those unproductive processor cycles not used by any other threads.
<b>Cache Hit Ratio</b>	The percentage of time that a requested data page was found in the data cache (instead of being read from disk).
<b>I/O - Batch Writes/sec</b>	The number of pages written to disk per second, using Batch I/O. The checkpoint thread is the primary user of Batch I/O.
<b>I/O - Lazy Writes/sec</b>	The number of pages flushed to disk per second by the Lazy Writer.
<b>I/O - Outstanding Reads</b>	The number of physical reads pending.
<b>I/O - Outstanding Writes</b>	The number of physical writes pending.

, continued

Measurement	Description
I/O - Page Reads/sec	The number of physical page reads per second.
I/O - Transactions/sec	The number of Transact-SQL command batches executed per second.
User Connections	The number of open user connections.
% Processor Time	The percentage of time that the processor is executing a non-idle thread. This counter was designed as a primary indicator of processor activity. It is calculated by measuring the time that the processor spends executing the thread of the idle process in each sample interval, and subtracting that value from 100%. (Each processor has an idle thread which consumes cycles when no other threads are ready to run). It can be viewed as the percentage of the sample interval spent doing useful work. This counter displays the average percentage of busy time observed during the sample interval. It is calculated by monitoring the time the service was inactive, and then subtracting that value from 100%.

## Sybase Server Monitoring Measurements

The following tables describe the measurements that can be monitored on a Sybase server:

Object	Measurement	Description
<b>Network</b>	<b>Average packet size (Read)</b>	Reports the number of network packets received.
	<b>Average packet size (Send)</b>	Reports the number of network packets sent.
	<b>Network bytes (Read)</b>	Reports the number of bytes received, over the sampling interval.
	<b>Network bytes (Read)/sec</b>	Reports the number of bytes received, per second.
	<b>Network bytes (Send)</b>	Reports the number of bytes sent, over the sampling interval.
	<b>Network bytes (Send)/sec</b>	Reports the number of bytes sent, per second.
	<b>Network packets (Read)</b>	Reports the number of network packets received, over the sampling interval.
	<b>Network packets (Read)/sec</b>	Reports the number of network packets received, per second.
	<b>Network packets (Send)</b>	Reports the number of network packets sent, over the sampling interval.
	<b>Network packets (Send)/sec</b>	Reports the number of network packets sent, per second.
<b>Memory</b>	<b>Memory</b>	Reports the amount of memory (in bytes) allocated for the page cache.
<b>Disk</b>	<b>Reads</b>	Reports the number of reads made from a database device.
	<b>Writes</b>	Reports the number of writes made to a database device.
	<b>Waits</b>	Reports the number of times that access to a device had to wait.
	<b>Grants</b>	Reports the number of times access to a device was granted.

, continued

Object	Measurement	Description
Engine	<b>Server is busy (%)</b>	Reports the percentage of time during which the Adaptive Server is in a "busy" state.
	<b>CPU time</b>	Reports how much "busy" time was used by the engine.
	<b>Logical pages (Read)</b>	Reports the number of data page reads, whether satisfied from cache or from a database device.
	<b>Pages from disk (Read)</b>	Reports the number of data page reads that could not be satisfied from the data cache.
	<b>Pages stored</b>	Reports the number of data pages written to a database device.
Stored Procedures	<b>Executed (sampling period)</b>	Reports the number of times a stored procedure was executed, over the sampling interval.
	<b>Executed (session)</b>	Reports the number of times a stored procedure was executed, during the session.
	<b>Average duration (sampling period)</b>	Reports the time (in seconds) spent executing a stored procedure, over the sampling interval.
	<b>Average duration (session)</b>	Reports the time (in seconds) spent executing a stored procedure, during the session.
Locks	<b>% Requests</b>	Reports the percentage of successful requests for locks.
	<b>Locks count</b>	Reports the number of locks. This is an accumulated value.
	<b>Granted immediately</b>	Reports the number of locks that were granted immediately, without having to wait for another lock to be released.
	<b>Granted after wait</b>	Reports the number of locks that were granted after waiting for another lock to be released.
	<b>Not granted</b>	Reports the number of locks that were requested but not granted.
	<b>Wait time (avg.)</b>	Reports the average wait time for a lock.

, continued

Object	Measurement	Description
SqlSrvr	<b>Locks/sec</b>	Reports the number of locks. This is an accumulated value.
	<b>% Processor time (server)</b>	Reports the percentage of time that the Adaptive Server is in a "busy" state.
	<b>Transactions</b>	Reports the number of committed Transact-SQL statement blocks (transactions).
	<b>Deadlocks</b>	Reports the number of deadlocks.
Cache	<b>% Hits</b>	Reports the percentage of times that a data page read could be satisfied from cache without requiring a physical page read.
	<b>Pages (Read)</b>	Reports the number of data page reads, whether satisfied from cache or from a database device.
Cache	<b>Pages (Read) /sec</b>	Reports the number of data page reads, whether satisfied from cache or from a database device, per second.
	<b>Pages from disk (Read)</b>	Reports the number of data page reads that could not be satisfied from the data cache.
	<b>Pages from disk (Read)/sec</b>	Reports the number of data page reads, per second, that could not be satisfied from the data cache.
	<b>Pages (Write)</b>	Reports the number of data pages written to a database device.
	<b>Pages (Write) /sec</b>	Reports the number of data pages written to a database device, per second.
Process	<b>% Processor time (process)</b>	Reports the percentage of time that a process running a given application was in the "Running" state (out of the time that all processes were in the "Running" state).
	<b>Locks/sec</b>	Reports the number of locks, by process. This is an accumulated value.
	<b>% Cache hit</b>	Reports the percentage of times that a data page read could be satisfied from cache without requiring a physical page read, by process.
	<b>Pages (Write)</b>	Reports the number of data pages written to a database device, by process.
Transaction	<b>Transactions</b>	Reports the number of committed Transact-SQL statement blocks (transactions), during the session.

, continued

Object	Measurement	Description
<b>Transaction</b>	<b>Rows (Deleted)</b>	Reports the number of rows deleted from database tables during the session.
	<b>Inserts</b>	Reports the number of insertions into a database table during the session.
	<b>Updates</b>	Reports the updates to database tables during the session.
	<b>Updates in place</b>	Reports the sum of expensive, in-place and not-in-place updates (everything except updates deferred) during the session.
	<b>Transactions/sec</b>	Reports the number of committed Transact-SQL statement blocks (transactions) per second.
	<b>Rows (Deleted) /sec</b>	Reports the number of rows deleted from database tables, per second.
	<b>Inserts/sec</b>	Reports the number of insertions into a database table, per second.
	<b>Updates/sec</b>	Reports the updates to database tables, per second.
	<b>Updates in place/sec</b>	Reports the sum of expensive, in-place and not-in-place updates (everything except updates deferred), per second.

## DB2 Graph

This graph shows the resource usage on the DB2 database server machine as a function of the elapsed load test scenario time.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the DB2 database server.
<b>Note</b>	In order to monitor the DB2 database server machine, you must first set up the DB2 monitor environment. You then enable the DB2 monitor (from the Controller) by selecting the counters you want the monitor to measure.
<b>See also</b>	<a href="#">"Database Server Resource Graphs Overview" on page 1554</a> <a href="#">"DB2 Database Manager Counters" on page 1555</a> <a href="#">"DB2 Database Counters" on page 1556</a> <a href="#">"DB2 Application Counters" on page 1561</a>


## Oracle Graph

This graph displays information from Oracle V\$ tables: Session statistics, V\$SESSTAT, system statistics, V\$SYSSTAT, and other table counters defined by the user in the custom query.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the Oracle server.
Note	To obtain data for this graph, you need to enable the Oracle online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Database Server Resource Graphs Overview" on page 1554</a> <a href="#">"Oracle Server Monitoring Measurements" on page 1566</a>

### Example

In the following example, the V\$SYSSTAT resource values are shown as a function of the elapsed load test scenario time:




## SQL Server Graph

This graph shows the standard Windows resources on the SQL server machine.

X-axis	Elapsed time since the start of the load test scenario run.
--------	-------------------------------------------------------------

<b>Y-axis</b>	Resource usage
<b>Note</b>	To obtain data for this graph, you need to enable the SQL Server online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"Database Server Resource Graphs Overview" on page 1554</a> <a href="#">"SQL Server Default Counters" on page 1567</a>

### Example



## Sybase Graph

This graph shows the resource usage on the Sybase database server machine as a function of the elapsed load test scenario time.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the Sybase database server.
<b>Note</b>	In order to monitor the Sybase database server machine, you must first set up the Sybase monitor environment. You then enable the Sybase monitor (from the Controller) by selecting the counters you want the monitor to measure.
<b>See also</b>	<a href="#">"Database Server Resource Graphs Overview" on page 1554</a> <a href="#">"SQL Server Default Counters" on page 1567</a>

# Streaming Media Graphs

## Streaming Media Graphs Overview

Streaming Media Resource graphs provide you with performance information for the RealPlayer Client, RealPlayer Server, Windows Media Server, and Media Player Client machines.

In order to obtain data for Streaming Media Resource graphs, you need to install the RealPlayer Client and activate the online monitor for the RealPlayer Server or Windows Media Server before running the load test scenario.

When you set up the online monitor for the RealPlayer Server or Windows Media Server, you indicate which statistics and measurements to monitor. For more information on installing and configuring the Streaming Media Resource monitors, refer to the *HP LoadRunner Controller User Guide*.

In order to display all the measurements on a single graph, Analysis may scale them. The Legend window indicates the scale factor for each resource. To obtain the true value, multiply the scale factor by the displayed value.

## Media Player Client Monitoring Measurements

The following table describes the Media Player Client measurements that are monitored:

Measurement	Description
Average Buffering Events	The number of times Media Player Client had to buffer incoming media data due to insufficient media content.
Average Buffering Time (sec)	The time spent by Media Player Client waiting for sufficient amount of media data in order to continue playing media clip.
Current bandwidth (Kbits/sec)	The number of kbits per second received.
Number of Packets	The number of packets sent by server for a particular media clip.
Stream Interruptions	The number of interruptions encountered by Media Player Client while playing a media clip. This measurement includes the number of times Media Player Client had to buffer incoming media data, and any errors that occurred during playback.
Stream Quality (Packet-level)	The percentage ratio of packets received to total packets.

, continued

Measurement	Description
<b>Stream Quality (Sampling-level)</b>	The percentage of stream samples received on time (no delays in reception).
<b>Total number of recovered packets</b>	The number of lost packets that were recovered. This value is only relevant during network playback.
<b>Total number of lost packets</b>	The number of lost packets that were not recovered. This value is only relevant during network playback.

## **RealPlayer Client Monitoring Measurements**

The following table describes the RealPlayer Client measurements that are monitored:

Measurement	Description
<b>Current Bandwidth (Kbits/sec)</b>	The number of kilobytes in the last second.
<b>Buffering Event Time (sec)</b>	The average time spent on buffering.
<b>Network Performance</b>	The ratio (percentage) between the current bandwidth and the actual bandwidth of the clip.
<b>Percentage of Recovered Packets</b>	The percentage of error packets that were recovered.
<b>Percentage of Lost Packets</b>	The percentage of packets that were lost.
<b>Percentage of Late Packets</b>	The percentage of late packets.
<b>Time to First Frame Appearance (sec)</b>	The time for first frame appearance (measured from the start of the replay).
<b>Number of Buffering Events</b>	The average number of all buffering events.
<b>Number of Buffering Seek Events</b>	The average number of buffering events resulting from a seek operation.
<b>Buffering Seek Time</b>	The average time spent on buffering events resulting from a seek operation.
<b>Number of Buffering Congestion Events</b>	The average number of buffering events resulting from network congestion.

, continued

Measurement	Description
<b>Buffering Congestion Time</b>	The average time spent on buffering events resulting from network congestion.
<b>Number of Buffering Live Pause Events</b>	The average number of buffering events resulting from live pause.
<b>Buffering Live Pause Time</b>	The average time spent on buffering events resulting from live pause.

## **RealPlayer Server Monitoring Measurements**

The following table describes the RealPlayer Client measurements that are monitored:

Measurement	Description
<b>Current Bandwidth (Kbits/sec)</b>	The number of kilobytes in the last second.
<b>Buffering Event Time (sec)</b>	The average time spent on buffering.
<b>Network Performance</b>	The ratio (percentage) between the current bandwidth and the actual bandwidth of the clip.
<b>Percentage of Recovered Packets</b>	The percentage of error packets that were recovered.
<b>Percentage of Lost Packets</b>	The percentage of packets that were lost.
<b>Percentage of Late Packets</b>	The percentage of late packets.
<b>Time to First Frame Appearance (sec)</b>	The time for first frame appearance (measured from the start of the replay).
<b>Number of Buffering Events</b>	The average number of all buffering events.
<b>Number of Buffering Seek Events</b>	The average number of buffering events resulting from a seek operation.
<b>Buffering Seek Time</b>	The average time spent on buffering events resulting from a seek operation.
<b>Number of Buffering Congestion Events</b>	The average number of buffering events resulting from network congestion.
<b>Buffering Congestion Time</b>	The average time spent on buffering events resulting from network congestion.
<b>Number of Buffering Live Pause Events</b>	The average number of buffering events resulting from live pause.

, continued

Measurement	Description
<b>Buffering Live Pause Time</b>	The average time spent on buffering events resulting from live pause.

## Windows Media Server Default Measurements

Measurement	Description
<b>Active Live Unicast Streams (Windows)</b>	The number of live unicast streams that are being streamed.
<b>Active Streams</b>	The number of streams that are being streamed.
<b>Active TCP Streams</b>	The number of TCP streams that are being streamed.
<b>Active UDP Streams</b>	The number of UDP streams that are being streamed.
<b>Aggregate Read Rate</b>	The total, aggregate rate (bytes/sec) of file reads.
<b>Aggregate Send Rate</b>	The total, aggregate rate (bytes/sec) of stream transmission.
<b>Connected Clients</b>	The number of clients connected to the server.
<b>Connection Rate</b>	The rate at which clients are connecting to the server.
<b>Controllers</b>	The number of controllers currently connected to the server.
<b>HTTP Streams</b>	The number of HTTP streams being streamed.
<b>Late Reads</b>	The number of late read completions per second.
<b>Pending Connections</b>	The number of clients that are attempting to connect to the server, but are not yet connected. This number may be high if the server is running near maximum capacity and cannot process a large number of connection requests in a timely manner.
<b>Stations</b>	The number of station objects that currently exist on the server.
<b>Streams</b>	The number of stream objects that currently exist on the server.
<b>Stream Errors</b>	The cumulative number of errors occurring per second.


## Media Player Client Graph

This graph shows statistics on the Windows Media Player client machine as a function of the elapsed load test scenario time.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the Windows Media Player client machine.
<b>See also</b>	<a href="#">"Streaming Media Graphs Overview" on page 1575</a> <a href="#">"Media Player Client Monitoring Measurements" on page 1575</a>

### Example

In the following example the **Total number of recovered packets** remained steady during the first two and a half minutes of the scenario. The **Number of Packets** and **Stream Interruptions** fluctuated significantly. The **Average Buffering Time** increased moderately, and the **Player Bandwidth** increased and then decreased moderately. The scale factor for the **Stream Interruptions** and **Average Buffering Events** measurements is 10, and the scale factor for **Player Bandwidth** is 1/10.




## Real Client Graph

This graph shows statistics on the RealPlayer client machine as a function of the elapsed load test scenario time.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the RealPlayer client machine.
<b>See also</b>	<a href="#">"Streaming Media Graphs Overview" on page 1575</a> <a href="#">"RealPlayer Client Monitoring Measurements" on page 1576</a>

### Example

In the following example this graph displays the **Total Number of Packets**, **Number of Recovered Packets**, **Current Bandwidth**, and **First Frame Time** measurements during the first four and a half minutes of the scenario. The scale factor is the same for all of the measurements.




## Real Server Graph

This graph shows RealPlayer server statistics as a function of the elapsed load test scenario time.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage of the RealPlayer server machine.
<b>Note</b>	To obtain data for this graph, you need to enable the RealPlayer Server online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"Streaming Media Graphs Overview" on page 1575</a> <a href="#">"RealPlayer Server Monitoring Measurements" on page 1577</a>

### Example

In the following example this graph displays the **Total Number of Packets**, **Number of Recovered Packets**, **Current Bandwidth**, and **First Frame Time** measurements during the first four and a half minutes of the scenario. The scale factor is the same for all of the measurements.



## Windows Media Server Graph

This graph shows the Windows Media server statistics as a function of the elapsed load test scenario time.

X-axis	Elapsed time since the start of the run.
Y-axis	Resource usage.
Note	To obtain data for this graph, you need to enable the Windows Media Server online monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Streaming Media Graphs Overview" on page 1575</a> <a href="#">"Windows Media Server Default Measurements" on page 1578</a>

## ERP/CRM Server Resource Graphs

## ERP/CRM Server Resource Graphs Overview

ERP/CRM server resource monitor graphs provide you with performance information for ERP/CRM servers. To obtain data for these graphs, you must activate the ERP/CRM server resource online monitor before running the scenario. When you set up the online monitor for ERP/CRM server resources, you indicate which statistics and measurements to monitor. For more information on activating and configuring ERP/CRM server resource monitors, refer to the *HP LoadRunner Controller User Guide*.

**Note:** ERP/CRM Diagnostics graphs will only appear as an option in the Analysis “Add Graph” dialog if the scenario results contain relevant data.

## ERP/CRM Server Resources Graphs Measurements

### Tuxedo Graph Counters

The following table describes the default counters that can be measured. It is recommended to pay particular attention to the following measurements: % Busy Clients, Active Clients, Busy Clients, Idle Clients, and all the queue counters for the APPQ/PSAPPSRV queue.

Monitor	Measurements
Machine	<b>% Busy Clients.</b> The percentage of active clients currently logged in to the Tuxedo application server that are waiting for a response from the application server.
	<b>Active Clients.</b> The total number of active clients currently logged in to the Tuxedo application server.
	<b>Busy Clients.</b> The total number of active clients currently logged in to the Tuxedo application server that are waiting for a response from the application server.
	<b>Current Accessers.</b> The number of clients and servers currently accessing the application either directly on this machine or through a workstation handler on this machine.
	<b>Current Transactions.</b> The number of in use transaction table entries on this machine.
	<b>Idle Clients.</b> The total number of active clients currently logged in to the Tuxedo application server that are not waiting for a response from the application server.
	<b>Workload Completed/second.</b> The total workload on all the servers for the machine that was completed, per unit time.
	<b>Workload Initiated/second.</b> The total workload on all the servers for the machine that was initiated, per unit time.

, continued

Monitor	Measurements
Queue	<b>% Busy Servers.</b> The percentage of active servers currently handling Tuxedo requests.
	<b>Active Servers.</b> The total number of active servers either handling or waiting to handle Tuxedo requests.
	<b>Busy Servers.</b> The total number of active servers currently busy handling Tuxedo requests.
	<b>Idle Servers.</b> The total number of active servers currently waiting to handle Tuxedo requests.
	<b>Number Queued.</b> The total number of messages which have been placed on the queue.
Server	<b>Requests/second.</b> The number of server requests handled per second
	<b>Workload/second.</b> The workload is a weighted measure of the server requests. Some requests could have a different weight than others. By default, the workload is always 50 times the number of requests.
Workstation Handler (WSH)	<b>Bytes Received/sec.</b> The total number of bytes received by the workstation handler, per second.
	<b>Bytes Sent/sec.</b> The total number of bytes sent back to the clients by the workstation handler, per second.
	<b>Messages Received/sec.</b> The number of messages received by the workstation handler, per second.
	<b>Messages Sent/sec.</b> The number of messages sent back to the clients by the workstation handler, per second.
	<b>Number of Queue Blocks/sec.</b> The number of times the queue for the workstation handler blocked, per second. This gives an idea of how often the workstation handler was overloaded.

## SAP Server Graph Counters

The following are the most commonly monitored counters for a SAP server:

Measurement	Description
Average CPU time	The average CPU time used in the work process.

, continued

Measurement	Description
<b>Average response time</b>	The average response time, measured from the time a dialog sends a request to the dispatcher work process, through the processing of the dialog, until the dialog is completed and the data is passed to the presentation layer. The response time between the SAP GUI and the dispatcher is not included in this value.
<b>Average wait time</b>	The average amount of time that an unprocessed dialog step waits in the dispatcher queue for a free work process. Under normal conditions, the dispatcher work process should pass a dialog step to the application process immediately after receiving the request from the dialog step. Under these conditions, the average wait time would be a few milliseconds. A heavy load on the application server or on the entire system causes queues at the dispatcher queue.
<b>Average load time</b>	The time needed to load and generate objects, such as ABAP source code and screen information, from the database.
<b>Database calls</b>	The number of parsed requests sent to the database.
<b>Database requests</b>	The number of logical ABAP requests for data in the database. These requests are passed through the R/3 database interface and parsed into individual database calls. The proportion of database calls to database requests is important. If access to information in a table is buffered in the SAP buffers, database calls to the database server are not required. Therefore, the ratio of calls/requests gives an overall indication of the efficiency of table buffering. A good ratio would be 1:10.
<b>Roll ins</b>	The number of rolled-in user contexts.
<b>Roll outs</b>	The number of rolled-out user contexts.
<b>Roll in time</b>	The processing time for roll ins.
<b>Roll out time</b>	The processing time for roll outs.
<b>Roll wait time</b>	The queue time in the roll area. When synchronous RFCs are called, the work process executes a roll out and may have to wait for the end of the RFC in the roll area, even if the dialog step is not yet completed. In the roll area, RFC server programs can also wait for other RFCs sent to them.
<b>Average time per logical DB call</b>	The average response time for all commands sent to the database system (in milliseconds). The time depends on the CPU capacity of the database server, the network, the buffering, and on the input/output capabilities of the database server. Access times for buffered tables are many magnitudes faster and are not considered in the measurement.

## SAPGUI Graph Counters

The following are the most commonly monitored counters:

Measurement	Description
<b>Average CPU time</b>	The average CPU time used in the work process.
<b>Average response time</b>	The average response time, measured from the time a dialog sends a request to the dispatcher work process, through the processing of the dialog, until the dialog is completed and the data is passed to the presentation layer. The response time between the SAPGUI and the dispatcher is not included in this value.
<b>Average wait time</b>	The average amount of time that an unprocessed dialog step waits in the dispatcher queue for a free work process. Under normal conditions, the dispatcher work process should pass a dialog step to the application process immediately after receiving the request from the dialog step. Under these conditions, the average wait time would be a few milliseconds. A heavy load on the application server or on the entire system causes queues at the dispatcher queue.
<b>Average load time</b>	The time needed to load and generate objects, such as ABAP source code and screen information, from the database.
<b>Database calls</b>	The number of parsed requests sent to the database.
<b>Database requests</b>	The number of logical ABAP requests for data in the database. These requests are passed through the R/3 database interface and parsed into individual database calls. The proportion of database calls to database requests is important. If access to information in a table is buffered in the SAP buffers, database calls to the database server are not required. Therefore, the ratio of calls/requests gives an overall indication of the efficiency of table buffering. A good ratio would be 1:10.
<b>Roll ins</b>	The number of rolled-in user contexts.
<b>Roll outs</b>	The number of rolled-out user contexts.
<b>Roll in time</b>	The processing time for roll ins.
<b>Roll out time</b>	The processing time for roll outs.
<b>Roll wait time</b>	The queue time in the roll area. When synchronous RFCS are called, the work process executes a roll out and may have to wait for the end of the RFC in the roll area, even if the dialog step is not yet completed. In the roll area, RFC server programs can also wait for other RFCS sent to them.

, continued

Measurement	Description
<b>Average time per logical DB call</b>	The average response time for all commands sent to the database system (in milliseconds). The time depends on the CPU capacity of the database server, the network, the buffering, and on the input/output capabilities of the database server. Access times for buffered tables are many magnitudes faster and are not considered in the measurement.

## SAP Portal Graph Counters

The following are the monitored counters for a SAP Portal system server:

Measurement	Description
<b>Accumulated Amount of Outbound Data (bytes)</b>	The accumulated amount of outbound data, measured in bytes.
<b>Time for all Requests (ms)</b>	The total time (in milliseconds) taken for processing all requests.
<b>Average Amount of Outbound Data per Request (bytes)</b>	The average amount of outbound data per request, measured in bytes.
<b>Average Number of Component Calls per Request (bytes)</b>	The average number of component calls per request, measured in bytes.
<b>Average Time of a Request (ms)</b>	The average amount of time (in milliseconds) taken to process a request.
<b>Number of Calls with Outbound Data</b>	The total number of calls with outbound data.
<b>Number of Component Calls for all Requests</b>	The total number of component calls for all requests.
<b>Number of Requests since First Request</b>	The total number of requests since the first request was made.
<b>Requests per Second</b>	The number of requests made per second.
<b>Time Stamp of First Request</b>	The time stamp of the first request.

## Siebel Server Manager Graph Counters

The following are the monitored counters for a Siebel Server Manager server.

Measurement	Description
<b>Average Connect Time</b>	The average connection time.
<b>Average Reply Size</b>	The average size of a user reply.

, continued

<b>Measurement</b>	<b>Description</b>
<b>Average Request Size</b>	The average size of a user request.
<b>Average Requests Per Session</b>	The average number of user requests per session.
<b>Average Response Time</b>	The average amount of time that it takes the server to respond to a request.
<b>Average Think Time</b>	The average amount of think time taken to respond to a request.
<b>Avg SQL Execute Time</b>	The average SQL execute time.
<b>Avg SQL Fetch Time</b>	The average SQL fetch time.
<b>Avg SQL Parse Time</b>	The average SQL parse time.
<b>CPU Time</b>	The CPU time used in the work process.
<b>Elapsed Time</b>	The total amount of elapsed time.
<b>Num of DBConn Retries</b>	The number of database connection retries.
<b>Num of DLRbk Retries</b>	The number of DLRbk retries.
<b>Num of Exhausted Retries</b>	The total number of retries that expired.
<b>Number of SQL Executes</b>	The total number of SQL executes.
<b>Number of SQL Fetches</b>	The total number of SQL fetches.
<b>Number of SQL Parses</b>	The total number of SQL parses.
<b>Number of Sleeps</b>	The number of sleeps.
<b>Object Manager Errors</b>	The total number of object manager errors.
<b>Reply Messages</b>	The total number of reply messages.
<b>Request Messages</b>	The total number of request messages.
<b>SQL Execute Time</b>	The total SQL execute time.
<b>SQL Fetch Time</b>	The total SQL fetch time.
<b>SQL Parse Time</b>	The total SQL parse time.
<b>Sleep Time</b>	The total sleep time.
<b>Tests Attempted</b>	The number of tests attempted.
<b>Tests Failed</b>	The number of tests that failed.

, continued

Measurement	Description
<b>Tests Successful</b>	The number of tests that were successful.
<b>Total Reply Size</b>	The total reply size, measured in bytes.
<b>Total Request Size</b>	The total request size, measured in bytes.
<b>Total Response Time</b>	The total response time.
<b>Total Tasks</b>	The total number of tasks.
<b>Total Think Time</b>	The total think time.

## Siebel Web Server Graph Counters

The following are the monitored counters for a Siebel Web Server:

Measurement	Description
<b>Anonymous sessions requested from the pool</b>	The number of anonymous sessions requested from the pool.
<b>Open Session Time</b>	The time taken for users to log on to the system.
<b>Anon Session Removed</b>	The number of anonymous sessions removed from the pool.
<b>Anon Session Available</b>	The number of anonymous sessions available in the pool.
<b>Anonymous sessions returns to the pool</b>	The number of anonymous sessions returned to the pool.
<b>Response Time</b>	The time taken to respond to a user request.
<b>Close Session Time</b>	The time taken for users to log off the system.
<b>Request Time</b>	The time taken to process the user request.


## Tuxedo Graph

This graph shows the resource usage of your Tuxedo server as a function of the elapsed load test scenario time

<b>X-axis</b>	Elapsed time from the start of the run.
<b>Y-axis</b>	The resource usage on the Tuxedo server.

<b>Note</b>	To obtain data for this graph, you need to enable the Tuxedo monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a> <a href="#">"ERP/CRM Server Resources Graphs Measurements" on page 1582</a>


### Example



## SAP Graph

This graph shows the resource usage of a SAP server as a function of the elapsed load test scenario time.


<b>X-axis</b>	Elapsed time since the start of the run
<b>Y-axis</b>	The resource usage on the SAP server.
<b>Note</b>	To obtain data for this graph, you need to enable the SAP online monitor (from the Controller) and select the default measurements you want to display, before running the scenario. (There are differences in the scale factor for some of the measurements).
<b>See also</b>	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a> <a href="#">"ERP/CRM Server Resources Graphs Measurements" on page 1582</a>



## SAPGUI Graph

This graph shows the resource usage of a SAP server as a function of the elapsed load test scenario time.


<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the SAP server.
<b>Note</b>	To obtain data for this graph, you need to enable the SAP online monitor (from the Controller) and select the default measurements you want to display, before running the scenario. (There are differences in the scale factor for some of the measurements).
<b>See also</b>	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a> <a href="#">"ERP/CRM Server Resources Graphs Measurements" on page 1582</a>



## SAP CCMS Graph

The SAP CCMS (Computer Center Management System) graph shows statistics about the resource usage of all the servers in a SAP R/3 landscape server during the load test scenario run. The x-axis represents the time that has elapsed since the start of the scenario run. The y-axis represents the resource usage.


<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on all servers in a SAP R/3 landscape server.
<b>Note</b>	To obtain data for this graph, you need to enable the SAP CCMS monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a>



## SAP Portal Graph

This graph shows the resource usage of your SAP Portal server as a function of the elapsed load test scenario time.


<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the SAP Portal server.
<b>Note</b>	To obtain data for this graph, you need to enable the SAP Portal monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a> <a href="#">"ERP/CRM Server Resources Graphs Measurements" on page 1582</a>



## Siebel Server Manager Graph

This graph shows the resource usage of your Siebel Server Manager server as a function of the elapsed load test scenario time.


X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the Siebel Server Manager server.
Note	To obtain data for this graph, you need to enable the Siebel Server Manager monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a> <a href="#">"ERP/CRM Server Resources Graphs Measurements" on page 1582</a>



## Siebel Web Server Graph

This graph shows the resource usage of your Siebel Web Server as a function of the elapsed load test scenario time.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage on the Siebel Web Server.
Note	To obtain data for this graph, you need to enable the Siebel Web Server monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"ERP/CRM Server Resource Graphs Overview" on page 1582</a> <a href="#">"ERP/CRM Server Resources Graphs Measurements" on page 1582</a>



## Application Component Graphs

### **Microsoft COM+ Performance Graphs Overview**

Microsoft COM+ performance graphs provide you with performance information for COM+ interfaces and methods.

In order to obtain data for these graphs, you need to activate the various Microsoft COM+ performance monitors before running the load test scenario.

When you set up the Microsoft COM+ performance online monitors, you indicate which statistics and measurements to monitor. For more information on activating and configuring the Microsoft COM+ performance monitors, refer to the *HP LoadRunner Controller User Guide*.

### **Microsoft .NET CLR Performance Graphs Overview**


The .NET CLR performance graphs provide you with performance information for .NET classes and methods. To obtain data for these graphs, you must activate the .NET CLR performance monitor before running the load test scenario run.

Displayed measurements are specified using the .NET monitor. For more information on activating and configuring the .NET CLR performance monitor, refer to the *HP LoadRunner Controller User Guide*.

## COM+ Average Response Time Graph

This graph specifies the average time COM+ interfaces or methods take to perform during the load test scenario.

<b>X-axis</b>	Elapsed time from the beginning of the scenario run.																								
<b>Y-axis</b>	Average response time of a COM+ interface or method.																								
<b>Breakdown options</b>	<p>Each interface or method is represented by a different colored line on the graph. The legend frame (which is found below the graph) identifies the interfaces by color:</p> <table border="1"><thead><tr><th>Color</th><th>Scale</th><th>Measurement</th><th>Minimum</th><th>Average</th><th>Maximum</th></tr></thead><tbody><tr><td><input checked="" type="checkbox"/></td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\Dispatch</td><td>0.096</td><td>0.499</td><td>1.501</td></tr><tr><td><input checked="" type="checkbox"/></td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\_ConstTime</td><td>0</td><td>0.5</td><td>1.502</td></tr><tr><td><input checked="" type="checkbox"/></td><td>1</td><td>ContrRnd\COMPlusServer.RandomTime\RandomTime</td><td>0.058</td><td>0.391</td><td>0.747</td></tr></tbody></table> <p>This legend shows that the blue colored line belongs to the COM+ interface <b>_ConstTime</b>. Looking at the graph above, we see that this interface has higher response times than all other COM+ interfaces. At 2:10 minutes into the scenario, it records an average response time of 0.87 seconds.</p> <p><b>Note:</b> The 0.87 second data point is an average, taken from all data points recorded within a 10 second interval (the default granularity). You can change the length of this sample interval.</p> <p><b>Viewing COM+ Methods</b></p> <p>The table initially displays COM+ interfaces, but you can also view the list of COM+ methods by using drill-down or filtering techniques. For more information, see "<a href="#">Filtering and Sorting Graph Data</a>" on page 1394 and "<a href="#">Drilling Down in a Graph</a>" on page 1412.</p>	Color	Scale	Measurement	Minimum	Average	Maximum	<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\Dispatch	0.096	0.499	1.501	<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	0	0.5	1.502	<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	0.058	0.391	0.747
Color	Scale	Measurement	Minimum	Average	Maximum																				
<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\Dispatch	0.096	0.499	1.501																				
<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	0	0.5	1.502																				
<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	0.058	0.391	0.747																				
<b>Tips</b>	To highlight a specific interface line in the graph, select the interface row in the legend.																								
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on the previous page																								




## ***COM+ Breakdown Graph***

This graph summarizes fundamental result data about COM+ interfaces or methods and presents it in table format.

<b>Purpose</b>	Using the COM+ Breakdown table, you can identify the COM+ interfaces or methods which consume the most time during the test. The table can be sorted by column, and the data can be viewed either by COM+ interface or COM+ method.
----------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------


<b>Breakdown options</b>	<p><b>Average Response Time</b></p> <p>The <b>Average Response Time</b> column shows how long, on average, an interface or method takes to perform. The graphical representation of this column is the "<a href="#">"COM+ Average Response Time Graph" on page 1596</a>".</p> <p><b>Call Count</b></p> <p>The next column, <b>Call Count</b>, specifies the number of times the interface or method was invoked. The graphical representation of this column is the "<a href="#">"COM+ Average Response Time Graph" on page 1596</a>".</p> <p><b>Total Response Time</b></p> <p>The final column, <b>Total Response Time</b>, specifies how much time was spent overall on the interface or method. It is calculated by multiplying the first two data columns together. The graphical representation of this column is the "<a href="#">"COM+ Average Response Time Graph" on page 1596</a>".</p> <p>The graphical representations of each of these columns are the "<a href="#">"COM+ Average Response Time Graph" on page 1596</a>", the "<a href="#">"COM+ Call Count Distribution Graph" on the next page</a>" and the "<a href="#">"COM+ Total Operation Time Distribution Graph" on page 1603</a>"</p> <p>Interfaces are listed in the <b>COM+ Interface</b> column in the form <b>Interface:Host</b>. In the table above, the <b>_ConstTime</b> interface took an average of .5 seconds to execute and was called 70 times. Overall, this interface took 34.966 seconds to execute.</p>
<b>Tips</b>	<p><b>Sorting List</b></p> <p>To sort the list by a column, click on the column heading. The list above is sorted by <b>Average Response Time</b> which contains the triangle icon specifying a sort in descending order.</p> <p><b>Viewing COM+ Methods</b></p> <p>The table initially displays COM+ interfaces, but you can also view the list of COM+ methods.</p> <p>To view the methods of a selected interface, select the <b>COM+ Methods</b> option. You can also double-click on the interface row to view the methods. The methods of the specified interface are listed in the <b>COM+ Method</b> column.</p>
<b>See also</b>	<p><a href="#">"Microsoft COM+ Performance Graphs Overview" on page 1595</a></p>



## ***COM+ Call Count Distribution Graph***


This graph shows the percentage of calls made to each COM+ interface compared to all COM+ interfaces. It can also show the percentage of calls made to a specific COM+ method compared to other methods within the interface.


<b>Breakdown options</b>	<p>The number of calls made to the interface or method is listed in the <b>Call Count</b> column of the "<a href="#">COM+ Breakdown Graph</a>" on page 1597 table.</p> <p>Each interface or method is represented by a different colored area on the pie graph. The legend frame (which is found below the graph) identifies the interfaces by color:</p> <table border="1"><thead><tr><th>Color</th><th>Scale</th><th>Measurement</th><th>Graph Average</th></tr></thead><tbody><tr><td>Green</td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\IDispatch</td><td>70</td></tr><tr><td>Blue</td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\_ConstTime</td><td>70</td></tr><tr><td>Yellow</td><td>1</td><td>ContrRnd\COMPlusServer.RandomTime\RandomTime</td><td>40</td></tr></tbody></table> <p>This legend shows that the green colored area belongs to the COM+ interface <b>IDispatch</b>. Looking at the graph above, we see that 38.89% of calls are made to this interface. The actual figures can be seen in the <b>Call Count</b> column of the "<a href="#">COM+ Breakdown Graph</a>" on page 1597 table: there are 13 calls to this interface out of a total of 49 calls.</p> <p><b>Viewing COM+ Methods</b></p> <p>The table initially displays COM+ interfaces, but you can also view the list of COM+ methods by using drill-down or filtering techniques. For more information, see "<a href="#">Filtering and Sorting Graph Data</a>" on page 1394 and "<a href="#">Drilling Down in a Graph</a>" on page 1412.</p>	Color	Scale	Measurement	Graph Average	Green	1	ContrRnd\COMPlusServer.ConstTime\IDispatch	70	Blue	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	70	Yellow	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	40
Color	Scale	Measurement	Graph Average														
Green	1	ContrRnd\COMPlusServer.ConstTime\IDispatch	70														
Blue	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	70														
Yellow	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	40														
<b>Tips</b>	To highlight a specific interface line in the graph, select the interface row in the legend.																
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595																



## COM+ Call Count Graph

This graph displays the number of times COM+ interfaces and methods are invoked during the test.

<b>X-axis</b>	Elapsed time from the beginning of the scenario run.																								
<b>Y-axis</b>	How many calls were made to a COM+ interface or method.																								
<b>Breakdown options</b>	Each interface or method is represented by a different colored line on the graph. The legend frame (which is found below the graph) identifies the interfaces by color:   <table border="1"><thead><tr><th>Color</th><th>Scale</th><th>Measurement</th><th>Graph Minimum</th><th>Average</th><th>Graph Maximum</th></tr></thead><tbody><tr><td></td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\Dispatch</td><td>0</td><td>1.777</td><td>13</td></tr><tr><td></td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\ConstTime</td><td>0</td><td>1.777</td><td>16</td></tr><tr><td></td><td>1</td><td>ContrRnd\COMPlusServer.RandomTime\RandomTime</td><td>0</td><td>1.015</td><td>20</td></tr></tbody></table> <p>This legend shows that the yellow colored line belongs to the COM+ interface <b>_RandomTime</b>. Looking at the graph above, we see that calls to this interface begin at the beginning of the scenario run. There are 20 calls at the 2:20 minute point.</p> <p><b>Viewing COM+ Methods</b></p> <p>The table initially displays COM+ interfaces, but you can also view the list of COM+ methods by using drill-down or filtering techniques. For more information, see "<a href="#">Filtering and Sorting Graph Data</a>" on page 1394 and "<a href="#">Drilling Down in a Graph</a>" on page 1412.</p>	Color	Scale	Measurement	Graph Minimum	Average	Graph Maximum		1	ContrRnd\COMPlusServer.ConstTime\Dispatch	0	1.777	13		1	ContrRnd\COMPlusServer.ConstTime\ConstTime	0	1.777	16		1	ContrRnd\COMPlusServer.RandomTime\RandomTime	0	1.015	20
Color	Scale	Measurement	Graph Minimum	Average	Graph Maximum																				
	1	ContrRnd\COMPlusServer.ConstTime\Dispatch	0	1.777	13																				
	1	ContrRnd\COMPlusServer.ConstTime\ConstTime	0	1.777	16																				
	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	0	1.015	20																				
<b>Note</b>	The call count is computed by multiplying the call frequency by a time interval. As a result, the reported measurement may be rounded.																								
<b>Tips</b>	To highlight a specific interface line in the graph, select the interface row in the legend.																								
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595																								



## COM+ Call Count Per Second Graph

This graph shows the number of times per second a COM+ interface or method is invoked.

### Breakdown options

This graph is similar to the "["COM+ Call Count Graph" on the previous page](#) except that the y-axis indicates how many invocations were made to a COM+ interface or method per second.

Each interface or method is represented by a different colored line on the graph. The legend frame (which is found below the graph) identifies the interfaces by color:


Color	Scale	Measurement	Graph Minimum	Average	Graph Maximum
<input checked="" type="checkbox"/>	1	ContRnd\COMPlusServer.ConstTime\IDispatch	0	0.355	2.6
<input checked="" type="checkbox"/>	1	ContRnd\COMPlusServer.ConstTime\ConstTime	0	0.355	3.2
<input checked="" type="checkbox"/>	1	ContRnd\COMPlusServer.RandomTime\RandomTime	0	0.203	4

This legend shows that the green colored line belongs to the COM+ interface **IDispatch**. Looking at the graph above, we see that calls to this interface begin 1:55 minutes into the scenario run. There is an average of 2.5 calls per second at the 2:10 minute mark.

### Viewing COM+ Methods

To view the average response time of the individual methods within a COM+ interface, see "[Filtering and Sorting Graph Data](#)" on page 1394 and "[Drilling Down in a Graph](#)" on page 1412.

<b>Tips</b>	To highlight a specific interface line in the graph, select the interface row in the legend.
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview" on page 1595</a>




## ***COM+ Total Operation Time Distribution Graph***

This graph shows the percentage of time a specific COM+ interface takes to execute in relation to all COM+ interfaces. It can also show the percentage of time a COM+ method takes to execute in relation to all COM+ methods within the interface.

<b>Purpose</b>	Use it to identify those interfaces or methods which take up an excessive amount of time.
----------------	-------------------------------------------------------------------------------------------


<b>Breakdown options</b>	Each interface or method is represented by a different colored area on the pie graph. The legend frame (which is found below the graph) identifies the interfaces by color:																
	<table border="1"><thead><tr><th>Color</th><th>Scale</th><th>Measurement</th><th>Graph Average</th></tr></thead><tbody><tr><td>Green</td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\IDispatch</td><td>34.936</td></tr><tr><td>Blue</td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\_ConstTime</td><td>34.966</td></tr><tr><td>Yellow</td><td>1</td><td>ContrRnd\COMPlusServer.RandomTime\_RandomTime</td><td>15.642</td></tr></tbody></table>	Color	Scale	Measurement	Graph Average	Green	1	ContrRnd\COMPlusServer.ConstTime\IDispatch	34.936	Blue	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	34.966	Yellow	1	ContrRnd\COMPlusServer.RandomTime\_RandomTime	15.642
Color	Scale	Measurement	Graph Average														
Green	1	ContrRnd\COMPlusServer.ConstTime\IDispatch	34.936														
Blue	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	34.966														
Yellow	1	ContrRnd\COMPlusServer.RandomTime\_RandomTime	15.642														
	This legend shows that the green colored line belongs to the COM+ interface <b>IDispatch</b> . Looking at the graph above, we see that this interface takes up 40.84% of the COM+ operational time.																
	<b>Viewing COM+ Methods</b>																
	To view the average response time of the individual methods within a COM+ interface, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.																
<b>Tips</b>	To highlight a specific interface line in the graph, select the interface row in the legend.																
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595																



## COM+ Total Operation Time Graph

This graph displays the amount of time each COM+ interface or method takes to execute during the test.

<b>Purpose</b>	Use it to identify those interfaces or methods which take up an excessive amount of time.																								
<b>X-axis</b>	Elapsed time from the beginning of the scenario run.																								
<b>Y-axis</b>	Total time a COM+ interface or method is in operation.																								
<b>Breakdown options</b>	<p>Each interface or method is represented by a different colored line on the graph. The legend frame (which is found below the graph) identifies the interfaces by color:</p> <table border="1"><thead><tr><th>Color</th><th>Scale</th><th>Measurement</th><th>Graph Minimum</th><th>Average</th><th>Graph Maximum</th></tr></thead><tbody><tr><td><input checked="" type="checkbox"/></td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\Dispatch</td><td>0</td><td>0.887</td><td>12.008</td></tr><tr><td><input checked="" type="checkbox"/></td><td>1</td><td>ContrRnd\COMPlusServer.ConstTime\_ConstTime</td><td>0</td><td>0.887</td><td>21.026</td></tr><tr><td><input checked="" type="checkbox"/></td><td>1</td><td>ContrRnd\COMPlusServer.RandomTime\RandomTime</td><td>0</td><td>0.397</td><td>8.24</td></tr></tbody></table> <p>This legend shows that the blue colored line belongs to the COM+ interface <b>_ConstTime</b>. Looking at the graph above, we see that throughout the scenario, this interface consumes more time than any other, especially at 2 minutes and 15 seconds into the scenario run, where the calls to this interface take an average of 21 seconds.</p> <p><b>Viewing COM+ Methods</b></p> <p>The table initially displays COM+ interfaces, but you can also view the list of COM+ methods by using drill-down or filtering techniques. For more information, see "<a href="#">Filtering and Sorting Graph Data</a>" on page 1394 and "<a href="#">Drilling Down in a Graph</a>" on page 1412.</p>	Color	Scale	Measurement	Graph Minimum	Average	Graph Maximum	<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\Dispatch	0	0.887	12.008	<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	0	0.887	21.026	<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	0	0.397	8.24
Color	Scale	Measurement	Graph Minimum	Average	Graph Maximum																				
<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\Dispatch	0	0.887	12.008																				
<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.ConstTime\_ConstTime	0	0.887	21.026																				
<input checked="" type="checkbox"/>	1	ContrRnd\COMPlusServer.RandomTime\RandomTime	0	0.397	8.24																				
<b>Tips</b>	To highlight a specific interface line in the graph, select the interface row in the legend.																								
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595																								




## Microsoft COM+ Graph

This graph shows the resource usage of COM+ objects as a function of the elapsed load test scenario time.

<b>X-axis</b>	Elapsed time since the start of the run.																																																															
<b>Y-axis</b>	The resource usage of COM+ objects.																																																															
<b>Breakdown Options</b>	Each COM+ object is represented by a different colored line on the graph. The legend frame (which is found below the graph) identifies the objects by color:																																																															
	<table border="1"> <thead> <tr> <th>Color</th> <th>Scale</th> <th>Measurement</th> <th>Minimum</th> <th>Average</th> <th>Maximum</th> <th>Std. Deviation</th> </tr> </thead> <tbody> <tr> <td>Green</td> <td>1</td> <td>ConfFindAuthenticate:dakota</td> <td>3.994</td> <td>12.482</td> <td>16.376</td> <td>3.84</td> </tr> <tr> <td>Black</td> <td>10</td> <td>ConfFind\COMPlusServer\ConstTime\Dispatch\Invoke\Method Duration:dakota</td> <td>0.096</td> <td>0.905</td> <td>1.501</td> <td>0.453</td> </tr> <tr> <td>Black</td> <td>10</td> <td>ConfFind\COMPlusServer\ConstTime\Dispatch\Invoke\Method Frequency:dakota</td> <td>0.399</td> <td>1.747</td> <td>2.596</td> <td>0.638</td> </tr> <tr> <td>Purple</td> <td>10</td> <td>ConfFind\COMPlusServer\ConstTime\Object Activate:dakota</td> <td>0.599</td> <td>1.997</td> <td>3.395</td> <td>1.398</td> </tr> <tr> <td>Blue</td> <td>10</td> <td>ConfFind\COMPlusServer\ConstTime\Object Create:dakota</td> <td>0.799</td> <td>3.995</td> <td>7.19</td> <td>3.195</td> </tr> <tr> <td>Yellow</td> <td>10</td> <td>ConfFind\COMPlusServer\ConstTime\Object Deactivate:dakota</td> <td>0.999</td> <td>1.988</td> <td>2.996</td> <td>0.998</td> </tr> <tr> <td>Yellow</td> <td>10</td> <td>ConfFind\COMPlusServer\ConstTime\Object Destroy:dakota</td> <td>0.999</td> <td>1.988</td> <td>2.996</td> <td>0.998</td> </tr> <tr> <td>Orange</td> <td>1</td> <td>ConfFind\COMPlusServer\ConstTime\Object InsertTime:dakota</td> <td>26.69</td> <td>26.495</td> <td>27.116</td> <td>0.736</td> </tr> </tbody> </table>	Color	Scale	Measurement	Minimum	Average	Maximum	Std. Deviation	Green	1	ConfFindAuthenticate:dakota	3.994	12.482	16.376	3.84	Black	10	ConfFind\COMPlusServer\ConstTime\Dispatch\Invoke\Method Duration:dakota	0.096	0.905	1.501	0.453	Black	10	ConfFind\COMPlusServer\ConstTime\Dispatch\Invoke\Method Frequency:dakota	0.399	1.747	2.596	0.638	Purple	10	ConfFind\COMPlusServer\ConstTime\Object Activate:dakota	0.599	1.997	3.395	1.398	Blue	10	ConfFind\COMPlusServer\ConstTime\Object Create:dakota	0.799	3.995	7.19	3.195	Yellow	10	ConfFind\COMPlusServer\ConstTime\Object Deactivate:dakota	0.999	1.988	2.996	0.998	Yellow	10	ConfFind\COMPlusServer\ConstTime\Object Destroy:dakota	0.999	1.988	2.996	0.998	Orange	1	ConfFind\COMPlusServer\ConstTime\Object InsertTime:dakota	26.69	26.495	27.116	0.736
Color	Scale	Measurement	Minimum	Average	Maximum	Std. Deviation																																																										
Green	1	ConfFindAuthenticate:dakota	3.994	12.482	16.376	3.84																																																										
Black	10	ConfFind\COMPlusServer\ConstTime\Dispatch\Invoke\Method Duration:dakota	0.096	0.905	1.501	0.453																																																										
Black	10	ConfFind\COMPlusServer\ConstTime\Dispatch\Invoke\Method Frequency:dakota	0.399	1.747	2.596	0.638																																																										
Purple	10	ConfFind\COMPlusServer\ConstTime\Object Activate:dakota	0.599	1.997	3.395	1.398																																																										
Blue	10	ConfFind\COMPlusServer\ConstTime\Object Create:dakota	0.799	3.995	7.19	3.195																																																										
Yellow	10	ConfFind\COMPlusServer\ConstTime\Object Deactivate:dakota	0.999	1.988	2.996	0.998																																																										
Yellow	10	ConfFind\COMPlusServer\ConstTime\Object Destroy:dakota	0.999	1.988	2.996	0.998																																																										
Orange	1	ConfFind\COMPlusServer\ConstTime\Object InsertTime:dakota	26.69	26.495	27.116	0.736																																																										

**See also** ["Microsoft COM+ Performance Graphs Overview" on page 1595](#)



## Authentication Metrics

Measurement	Description
<b>Authenticate</b>	Frequency of successful method call level authentication. When you set an authentication level for an application, you determine what degree of authentication is performed when clients call into the application.
<b>Authenticate Failed</b>	Frequency of failed method call level authentication.

## Application Event

Measurement	Description
<b>Activation</b>	Frequency of application activation or startup.
<b>Shutdown</b>	Frequency of application shutdown or termination.

## Thread Event

Measurement	Description
<b>Thread Start</b>	Rate at which single-threaded apartment (STA) thread for application have been started.
<b>Thread Terminate</b>	Rate at which single-threaded apartment (STA) thread for application have been terminated.
<b>Work Enque</b>	Event sent if a work is queued in single thread apartment object (STA). Note: These events are not signaled/sent in Windows Server 2003 and later.
<b>Work Reject</b>	Event sent if a work is rejected from single thread apartment object (STA). Note: These events are not signaled/sent in Windows Server 2003 and later.

## Transaction Events

Measurement	Description
<b>Transaction Duration</b>	Duration of COM+ transactions for selected application.
<b>Transaction Start</b>	Rate at which transactions have started.
<b>Transaction Prepared</b>	Rate at which transactions have completed the prepare phase of the two-phase protocol.
<b>Transaction Aborted</b>	Rate at which transactions have been aborted.
<b>Transaction Commit</b>	Rate at which transactions have completed the commit protocol.

## Object Events

Measurement	Description
<b>Object Life Time</b>	Duration of object existence (from instantiation to destruction).
<b>Object Create</b>	Rate at which new instances of this object are created.
<b>Object Destroy</b>	Rate at which instances of the object are destroyed.
<b>Object Activate</b>	Rate of retrieving instances of a new JIT-activated object.
<b>Object Deactivation</b>	Rate of freeing JIT-activated object via SetComplete or SetAbort.
<b>Disable Commit</b>	Rate of client calls to DisableCommit on a context. DisableCommit declares that the object's transactional updates are inconsistent and can't be committed in their present state.
<b>Enable Commit</b>	Rate of client calls to EnableCommit on a context. EnableCommit declares that the current object's work is not necessarily finished, but that its transactional updates are consistent and could be committed in their present form.
<b>Set Complete</b>	Rate of client calls to SetComplete on a context. SetComplete declares that the transaction in which the object is executing can be committed, and that the object should be deactivated on returning from the currently executing method call.

, continued

Measurement	Description
<b>Set Abort</b>	Rate of client calls to SetAbort on a context. SetAbort declares that the transaction in which the object is executing must be aborted, and that the object should be deactivated on returning from the currently executing method call.


## Method Events

Measurement	Description
<b>Method Duration</b>	Average duration of method.
<b>Method Frequency</b>	Frequency of method invocation.
<b>Method Failed</b>	Frequency of failed methods (i.e. methods that return error HRESULT codes).
<b>Method Exceptions</b>	Frequency of exceptions thrown by selected method.

## .NET Average Response Time Graph

This graph specifies the average time that .NET classes or methods took to perform during the load test scenario run.

<b>X-axis</b>	Elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	Average response time of a .NET class or method.
<b>Breakdown options</b>	The graph initially displays .NET classes, but you can also view the individual methods within a .NET class by using drill-down or filtering techniques. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.
<b>Tips</b>	You can change the length of the sample interval. For more information, refer to the <i>HP LoadRunner Controller User Guide</i> . <b>Hint:</b> To highlight a specific class line in the graph, select the class row in the legend (displayed below the graph).
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595




## **.NET Breakdown Graph**

This graph summarizes fundamental result data about .NET classes or methods and presents it in table format.

<b>Purpose</b>	Using the .NET Breakdown table, you can identify the .NET classes or methods which consume the most time during the test. The table can be sorted by column, and the data can be viewed either by .NET class or .NET method.
----------------	------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

<b>Breakdown options</b>	<p>The <b>Average Response Time</b> column shows how long, on average, a class or method took to perform. The next column, <b>Call Count</b>, specifies the number of times the class or method was invoked. The final column, <b>Total Response Time</b>, specifies how much time was spent overall on the class or method. It is calculated by multiplying the results from the first two columns together.</p> <p>Classes are listed in the <b>.NET Class</b> column in the form <b>Class:Host</b>. In the table above, the <b>AtmMachineSample.AtmTeller</b> class took an average of 783 seconds to execute and was called 50,912 times. Overall, this class took 39,316 seconds to execute.</p> <p>To sort the list by a column, click the column heading.</p> <p>Each column in the .NET Breakdown graph is graphically represented by another graph.</p> <p>The table initially displays .NET classes, but you can also view the list of .NET methods. To view .NET methods, select the <b>.NET Methods</b> option, or double-click the class row. The methods of the specified class are listed in the <b>.NET Method</b> column.</p>
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview" on page 1595</a>




## .NET Breakdown graph

.NET Breakdown Column	Graphical Representation
Average Response Time	.NET Average Response Time Graph.
Call Count	.NET Call Count Graph.
Total Response Time	.NET Total Operation Time Distribution Graph.

## .NET Call Count Distribution Graph

This graph shows the percentage of calls made to each .NET class compared to all .NET classes. It can also show the percentage of calls made to a specific .NET method compared to other methods within the class.


<b>Breakdown options</b>	The number of calls made to the class or method is listed in the <b>Call Count</b> column of the .NET Breakdown graph table.  The graph initially displays .NET classes, but you can also view the individual methods within a .NET class by using drill-down or filtering techniques. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.
<b>Tips</b>	To highlight a specific class line in the graph, select the class row in the legend (displayed below the graph).
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595



## .NET Call Count Graph

This graph displays the number of times that .NET classes and methods are invoked during the test.


<b>X-axis</b>	Elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	Indicates how many calls were made to a .NET class or method.
<b>Breakdown options</b>	The graph initially displays .NET classes, but you can also view the individual methods within a .NET class by using drill-down or filtering techniques. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.
<b>Tips</b>	To highlight a specific class line in the graph, select the class row in the legend (displayed below the graph).
<b>Note</b>	The call count is computed by multiplying the call frequency by a time interval. As a result, the reported measurement may be rounded.
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595



## .NET Call Count per Second Graph

This graph shows the number of times per second that a .NET class or method is invoked.


<b>Breakdown options</b>	This graph is similar to the .NET Call Count graph except that the y-axis indicates how many invocations were made to a .NET class or method per second. The graph initially displays .NET classes, but you can also view the individual methods within a .NET class by using drill-down or filtering techniques. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.
<b>Tips</b>	To highlight a specific class line in the graph, select the class row in the legend (displayed below the graph).
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595



## .NET Resources Graph

This graph shows the resource usage of .NET methods as a function of the elapsed load test scenario time.

<b>Breakdown options</b>	<p>Each .NET method is represented by a different colored line on the graph. The legend frame (located below the graph) identifies the methods by color:</p> <table border="1" data-bbox="452 321 1379 454"> <thead> <tr> <th>Color</th><th>Scale</th><th>Measurement</th><th>Minimum</th><th>Average</th><th>Maximum</th></tr> </thead> <tbody> <tr> <td></td><td>0.01</td><td>AtmMachineSample.dll\AtmMachineSample.At...</td><td>390.749</td><td>888.061</td><td>37848.727</td></tr> <tr> <td></td><td>10</td><td>AtmMachineSample.dll\AtmMachineSample.At...</td><td>1</td><td>4.244</td><td>10</td></tr> <tr> <td></td><td>0.1</td><td>AtmMachineSample.dll\AtmMachineSample.At...</td><td>190.944</td><td>194.783</td><td>207.318</td></tr> <tr> <td></td><td>10</td><td>AtmMachineSample.dll\AtmMachineSample.At...</td><td>1</td><td>4.235</td><td>10</td></tr> </tbody> </table>	Color	Scale	Measurement	Minimum	Average	Maximum		0.01	AtmMachineSample.dll\AtmMachineSample.At...	390.749	888.061	37848.727		10	AtmMachineSample.dll\AtmMachineSample.At...	1	4.244	10		0.1	AtmMachineSample.dll\AtmMachineSample.At...	190.944	194.783	207.318		10	AtmMachineSample.dll\AtmMachineSample.At...	1	4.235	10
Color	Scale	Measurement	Minimum	Average	Maximum																										
	0.01	AtmMachineSample.dll\AtmMachineSample.At...	390.749	888.061	37848.727																										
	10	AtmMachineSample.dll\AtmMachineSample.At...	1	4.244	10																										
	0.1	AtmMachineSample.dll\AtmMachineSample.At...	190.944	194.783	207.318																										
	10	AtmMachineSample.dll\AtmMachineSample.At...	1	4.235	10																										
	<p>You can monitor .NET counters at the application, assembly, class, and method levels. Measurements that take place before the application is fully loaded (such as Assembly Load Time, that measures the time it takes to load an assembly) will not be measured.</p> <p>The following tables describe the counters that can be measured at each level. All durations are reported in seconds, and all frequencies are reported per five-second polling periods. For example, if 20 events occur in a 5 second polling period, the reported frequency is 4.</p> <ul style="list-style-type: none"> <li>• <a href="#">"Application Level" on the next page</a></li> <li>• <a href="#">"Assembly Level" on page 1617</a></li> <li>• <a href="#">"Class Level" on page 1617</a></li> <li>• <a href="#">"Method Level" on page 1617</a></li> </ul>																														



## Application Level

Measurement	Description
<b>Application Lifetime</b>	Monitors the duration of the application in seconds.
<b>Exception Frequency</b>	Monitors the number of exceptions per second, in the five second polling period.
<b>JIT (Just In Time) Duration</b>	Monitors the time (in seconds) it takes for the JIT to compile code.
<b>Thread Creation Frequency</b>	Monitors the number of threads that are created in a polling period.
<b>Thread Lifetime</b>	Monitors the duration of threads.
<b>Domain Creation Frequency</b>	Monitors the number of domain creations in a polling period. (Domains protect areas of code. All applications run in a domain which keeps them encapsulated, so that they cannot interfere with other applications outside the domain.)
<b>Domain Load Time</b>	Monitors the time it takes to load a domain. (Domains protect areas of code. All applications run in a domain which keeps them encapsulated, so that they cannot interfere with other applications outside the domain).
<b>Domain Unload Time</b>	Monitors the time it takes to unload a domain. (Domains protect areas of code. All applications run in a domain which keeps them encapsulated, so that they cannot interfere with other applications outside the domain).
<b>Domain Lifetime</b>	Monitors the duration of a domain. (Domains protect areas of code. All applications run in a domain which keeps them encapsulated, so that they cannot interfere with other applications outside the domain).
<b>Module Creation Frequency</b>	Monitors the number of modules that get created in a polling period. (Modules are groups of assemblies that make up a DLL or EXE).
<b>Module Load Time</b>	Monitors the time it takes to load a module. (Modules are groups of assemblies that make up a dll or exe).
<b>Module Unload Time</b>	Monitors the time it takes to unload a module. (Modules are groups of assemblies that make up a dll or exe).
<b>Module Lifetime</b>	Monitors the duration of a module. (Modules are groups of assemblies that make up a dll or exe).

Measurement	Description
<b>Garbage Collection Duration</b>	Monitors the duration between the start and stop of Garbage Collection.
<b>Garbage Collection Frequency</b>	Monitors the number of breaks for Garbage Collections in a polling period.
<b>Unmanaged Code Duration</b>	Monitors the duration of the calls to unmanaged code.
<b>Unmanaged Code Frequency</b>	Monitors the number of calls to unengaged code in a polling period.

## Assembly Level

Measurement	Description
<b>Assembly Creation Frequency</b>	Monitors the number of assembly creations in a polling period. (Assemblies hold the .NET byte code and metadata).
<b>Assembly Load Time</b>	Monitors the time it takes to load an assembly. (Assemblies hold the .NET byte code and metadata).
<b>Assembly Unload Time</b>	Monitors the time it takes to unload an assembly. (Assemblies hold the .NET byte code and metadata).
<b>Assembly Lifetime</b>	Monitors the duration of an assembly. (Assemblies hold the .NET byte code and metadata).

## Class Level

Measurement	Description
<b>Class Lifetime</b>	Monitors the duration of a class.
<b>Class Load Time</b>	Monitors the time it takes to load a class.
<b>Class Unload Time</b>	Monitors the time it takes to unload a class.

## Method Level


At the method level, the measured time is per method, exclusive of other methods, calls to unmanaged code, and garbage collection time.

Measurement	Description
<b>Method Duration</b>	Monitors the duration of a method.
<b>Method Frequency</b>	Monitors the number of methods called in a polling period.

## **.NET Total Operation Time Distribution Graph**

This graph shows the percentage of time that a specific .NET class took to execute in relation to all the .NET classes. It can also show the percentage of time that a .NET method took to execute in relation to all the .NET methods within the class.


<b>Purpose</b>	Use this graph to identify those classes or methods that take an excessive amount of time.
<b>Breakdown options</b>	The graph initially displays .NET classes, but you can also view the individual methods within a .NET class by using drill-down or filtering techniques. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.
<b>Tips</b>	To highlight a specific class line in the graph, select the class row in the legend (displayed below the graph).
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595



## .NET Total Operation Time Graph

This graph displays the amount of time that each .NET class or method took to execute during the test.

<b>Purpose</b>	Use this graph to identify those classes or methods that take an excessive amount of time.
<b>X-axis</b>	Elapsed time from the beginning of the scenario run.
<b>Y-axis</b>	Total time a .NET class or method is in operation.
<b>Breakdown options</b>	The graph initially displays .NET classes, but you can also view the individual methods within a .NET class by using drill-down or filtering techniques. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394 and " <a href="#">Drilling Down in a Graph</a> " on page 1412.
<b>Tips</b>	To highlight a specific class line in the graph, select the class row in the legend (displayed below the graph).
<b>See also</b>	<a href="#">"Microsoft COM+ Performance Graphs Overview"</a> on page 1595



## Application Deployment Solutions Graphs

## **Application Deployment Solutions Graph Overview**

LoadRunner's Citrix MetaFrame XP monitor provides you with information about the application deployment usage of the Citrix MetaFrame XP server during a load test scenario execution. In order to obtain performance data, before you execute the scenario you need to activate the online monitor for the server and specify which resources you want to measure.

For more information on activating and configuring the Application Deployment Solutions monitor, refer to the *HP LoadRunner Controller User Guide*.

## **Citrix Measurements**

### **Non-Virtual Counters**

Measurement	Description
% Disk Time	The percentage of elapsed time that the selected disk drive services read or write requests.
% Processor Time	The percentage of time that the processor executes a non-Idle thread. This counter is a primary indicator of processor activity. It is calculated by measuring the time that the processor spends executing the thread of the Idle process in each sample interval, and subtracting that value from 100%. (Each processor has an Idle thread which consumes cycles when no other threads are ready to run.) It can be viewed as the percentage of the sample interval spent doing useful work. This counter displays the average percentage of busy time observed during the sample interval. It is calculated by monitoring the time the service was inactive, and then subtracting that value from 100%.
File data Operations/sec	The rate that the computer issues Read and Write operations to file system devices. It does not include File Control Operations.
Interrupts/sec	The average number of hardware interrupts the processor receives and services per second. It does not include DPCs, which are counted separately. This value is an indirect indicator of the activity of devices that generate interrupts, such as the system clock, the mouse, disk drivers, data communication lines, network interface cards and other peripheral devices. These devices normally interrupt the processor when they have completed a task or require attention. Normal thread execution is suspended during interrupts. Most system clocks interrupt the processor every 10 milliseconds, creating a background of interrupt activity. This counter displays the difference between the values observed in the last two samples, divided by the duration of the sample interval.
Output Session Line Speed	This value represents the line speed from server to client for a session in bps.

, continued

Measurement	Description
<b>Input Session Line Speed</b>	This value represents the line speed from client to server for a session in bps.
<b>Page Faults/sec</b>	A count of the Page Faults in the processor. A page fault occurs when a process refers to a virtual memory page that is not in its Working Set in main memory. A Page Fault will not cause the page to be fetched from disk if that page is on the standby list, and hence already in main memory, or if it is in use by another process with whom the page is shared.
<b>Pages/sec</b>	The number of pages read from the disk or written to the disk to resolve memory references to pages that were not in memory at the time of the reference. This is the sum of Pages Input/sec and Pages Output/sec. This counter includes paging traffic on behalf of the system Cache to access file data for applications. This value also includes the pages to/from non-cached mapped memory files. This is the primary counter to observe if you are concerned about excessive memory pressure (that is, thrashing), and the excessive paging that may result.
<b>Pool Nonpaged Bytes</b>	The number of bytes in the Nonpaged Pool, a system memory area where space is acquired by operating system components as they accomplish their appointed tasks. Nonpaged Pool pages cannot be paged out to the paging file, but instead remain in main memory as long as they are allocated.
<b>Private Bytes</b>	The current number of bytes this process has allocated that cannot be shared with other processes.
<b>Processor Queue Length</b>	The instantaneous length of the processor queue in units of threads. This counter is always 0 unless you are also monitoring a thread counter. All processors use a single queue in which threads wait for processor cycles. This length does not include the threads that are currently executing. A sustained processor queue length greater than two generally indicates processor congestion. This is an instantaneous count, not an average over the time interval.
<b>Threads</b>	The number of threads in the computer at the time of data collection. Notice that this is an instantaneous count, not an average over the time interval. A thread is the basic executable entity that can execute instructions in a processor.
<b>Latency – Session Average</b>	The average client latency over the life of a session.
<b>Latency – Last Recorded</b>	The last recorded latency measurement for this session.

, continued

Measurement	Description
<b>Latency – Session Deviation</b>	The difference between the minimum and maximum measured values for a session.
<b>Input Session Bandwidth</b>	The bandwidth (in bps) from client to server traffic for a session in bps.
<b>Input Session Compression</b>	The compression ratio for client to server traffic for a session.
<b>Output Session Bandwidth</b>	The bandwidth (in bps) from server to client traffic for a session.
<b>Output Session Compression</b>	The compression ratio for server to client traffic for a session.
<b>Output Session Linespeed</b>	The line speed (in bps) from server to client for a session.

## Virtual Channel Counters

All the counters in the following table are measured in bytes per second (bps):

Measurement	Description
<b>Input Audio Bandwidth</b>	The bandwidth from client to server traffic on the audio mapping channel.
<b>Input Clipboard Bandwidth</b>	The bandwidth from client to server traffic on the clipboard mapping channel.
<b>Input COM1 Bandwidth</b>	The bandwidth from client to server traffic on the COM1 channel.
<b>Input COM2 Bandwidth</b>	The bandwidth from client to server traffic on the COM2 channel.
<b>Input COM Bandwidth</b>	The bandwidth from client to server traffic on the COM channel.
<b>Input Control Channel Bandwidth</b>	The bandwidth from client to server traffic on the ICA control channel.
<b>Input Drive Bandwidth</b>	The bandwidth from client to server traffic on the client drive mapping channel.
<b>Input Font Data Bandwidth</b>	The bandwidth from client to server traffic on the local text echo font and keyboard layout channel.

, continued

Measurement	Description
<b>Input Licensing Bandwidth</b>	The bandwidth from server to client traffic on the licensing channel.
<b>Input LPT1 Bandwidth</b>	The bandwidth from client to server traffic on the LPT1 channel.
<b>Input LPT2 Bandwidth</b>	The bandwidth from client to server traffic on the LPT2 channel.
<b>Input Management Bandwidth</b>	The bandwidth from client to server traffic on the client management channel.
<b>Input PN Bandwidth</b>	The bandwidth from client to server traffic on the Program Neighborhood channel.
<b>Input Printer Bandwidth</b>	The bandwidth from client to server traffic on the printer spooler channel.
<b>Input Seamless Bandwidth</b>	The bandwidth from client to server traffic on the Seamless channel.
<b>Input Text Echo Bandwidth</b>	The bandwidth from client to server traffic on the local text echo data channel.
<b>Input Thinwire Bandwidth</b>	The bandwidth from client to server traffic on the Thinwire (graphics) channel.
<b>Input VideoFrame Bandwidth</b>	The bandwidth from client to server traffic on the VideoFrame channel.
<b>Output Audio Bandwidth</b>	The bandwidth from server to client traffic on the audio mapping channel.
<b>Output Clipboard Bandwidth</b>	The bandwidth from server to client traffic on the clipboard mapping channel.
<b>Output COM1 Bandwidth</b>	The bandwidth from server to client traffic on the COM1 channel.
<b>Output COM2 Bandwidth</b>	The bandwidth from server to client traffic on the COM2 channel.
<b>Output COM Bandwidth</b>	The bandwidth from server to client traffic on the COM channel.
<b>Output Control Channel Bandwidth</b>	The bandwidth from server to client traffic on the ICA control channel.
<b>Output Drive Bandwidth</b>	The bandwidth from server to client traffic on the client drive channel.


, continued

Measurement	Description
<b>Output Font Data Bandwidth</b>	The bandwidth from server to client traffic on the local text echo font and keyboard layout channel.
<b>Output Licensing Bandwidth</b>	The bandwidth from server to client traffic on the licensing channel.
<b>Output LPT1 Bandwidth</b>	The bandwidth from server to client traffic on the LPT1 channel.
<b>Output LPT2 Bandwidth</b>	The bandwidth from server to client traffic on the LPT2 channel.
<b>Output Management Bandwidth</b>	The bandwidth from server to client traffic on the client management channel.
<b>Output PN Bandwidth</b>	The bandwidth from server to client traffic on the Program Neighborhood channel.
<b>Output Printer Bandwidth</b>	The bandwidth from server to client traffic on the printer spooler channel.
<b>Output Seamless Bandwidth</b>	The bandwidth from server to client traffic on the Seamless channel.
<b>Output Text Echo Bandwidth</b>	The bandwidth from server to client traffic on the local text echo data channel.
<b>Output Thinwire Bandwidth</b>	The bandwidth from server to client traffic on the Thinwire (graphics) channel.
<b>Output VideoFrame Bandwidth</b>	The bandwidth from server to client traffic on the VideoFrame channel.

## Citrix MetaFrame XP Graph

This graph is an Application Deployment solution which delivers applications across networks. The Citrix MetaFrame Resource Monitor is an Application Deployment Solution monitor, which provides performance information for the Citrix MetaFrame server.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the Citrix MetaFrame server.
<b>Note</b>	To obtain data for this graph, you need to enable the Citrix MetaFrame XP monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"Application Deployment Solutions Graph Overview" on page 1620</a> <a href="#">"Citrix Measurements" on page 1620</a>



## Middleware Performance Graphs

### **Middleware Performance Graphs Overview**

A primary factor in a transaction's response time is the middleware performance usage. LoadRunner's Middleware Performance monitors provide you with information about the middleware performance usage of the Tuxedo and IBM WebSphere MQ servers during a load test scenario execution. To obtain performance data, you need to activate the online monitor for the server and specify which resources you want to measure before executing the scenario.

For more information on activating and configuring the Middleware Performance monitors, refer to the *HP LoadRunner Controller User Guide*.

### **IBM WebSphere MQ Counters**

#### **Queue Performance Counters**

Measurement	Description
<b>Event - Queue Depth High (events per second)</b>	An event triggered when the queue depth reaches the configured maximum depth.

, continued

Measurement	Description
<b>Event - Queue Depth Low (events per second)</b>	An event triggered when the queue depth reaches the configured minimum depth.
<b>Event - Queue Full (events per second)</b>	An event triggered when an attempt is made to put a message on a queue that is full.
<b>Event - Queue Service Interval High (events per second)</b>	An event triggered when no messages are put to or retrieved from a queue within the timeout threshold.
<b>Event - Queue Service Interval OK (events per second)</b>	An event triggered when a message has been put to or retrieved from a queue within the timeout threshold.
<b>Status - Current Depth</b>	The current count of messages on a local queue. This measurement applies only to local queues of the monitored queue manager.
<b>Status - Open Input Count</b>	The current count of open input handles. Input handles are opened so that an application may "put" messages to a queue.
<b>Status - Open Output Count</b>	The current count of open output handles. Output handles are opened so that an application may "get" messages from a queue.

## Channel Performance Counters

Measurement	Description
<b>Event - Channel Activated (events per second)</b>	An event generated when a channel, waiting to become active but inhibited from doing so due to a shortage of queue manager channel slots, becomes active due to the sudden availability of a channel slot.
<b>Event - Channel Not Activated (events per second)</b>	An event generated when a channel attempts to become active but is inhibited from doing so due to a shortage of queue manager channel slots.
<b>Event - Channel Started (events per second)</b>	An event generated when a channel is started.

, continued

Measurement	Description
<b>Event - Channel Stopped (events per second)</b>	An event generated when a channel is stopped, regardless of source of stoppage.
<b>Event - Channel Stopped by User (events per second)</b>	An event generated when a channel is stopped by a user.
<b>Status - Channel State</b>	The current state of a channel. Channels pass through several states from stopped (inactive state) to running (fully active state). Channel states range from 0 (stopped) to 6 (running).
<b>Status - Messages Transferred</b>	The count of messages that have been sent over the channel. If no traffic is occurring over the channel, this measurement will be zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Buffer Received</b>	The count of buffers that have been received over the channel. If no traffic is occurring over the channel, this measurement will be zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Buffer Sent</b>	The count of buffers that have been sent over the channel. If no traffic is occurring over the channel, this measurement will be zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Bytes Received</b>	The count of bytes that have been received over the channel. If no traffic is occurring over the channel, this measurement will appear as zero. If the channel has not been started since the queue manager was started, no measurement will be available.
<b>Status - Bytes Sent</b>	The count of bytes that have been sent over the channel. If no traffic is occurring over the channel, this measurement will appear as zero. If the channel has not been started since the queue manager was started, no measurement will be available.

## Tuxedo Resources Graph Measurements

The following table describes the default counters that can be measured. It is recommended to pay particular attention to the following measurements: % Busy Clients, Active Clients, Busy Clients, Idle Clients, and all the queue counters for relevant queues.

Monitor	Measurements
Machine	<b>% Busy Clients.</b> The percentage of active clients currently logged in to the Tuxedo application server that are waiting for a response from the application server.
	<b>Active Clients.</b> The total number of active clients currently logged in to the Tuxedo application server.
	<b>Busy Clients.</b> The total number of active clients currently logged in to the Tuxedo application server that are waiting for a response from the application server.
	<b>Current Accessers.</b> The number of clients and servers currently accessing the application either directly on this machine or through a workstation handler on this machine.
	<b>Current Transactions.</b> The number of in use transaction table entries on this machine.
	<b>Idle Clients.</b> The total number of active clients currently logged in to the Tuxedo application server that are not waiting for a response from the application server.
	<b>Workload Completed/second.</b> The total workload on all the servers for the machine that was completed, per unit time.
Queue	<b>Workload Initiated/second.</b> The total workload on all the servers for the machine that was initiated, per unit time.
	<b>% Busy Servers.</b> The percentage of active servers currently handling Tuxedo requests.
	<b>Active Servers.</b> The total number of active servers either handling or waiting to handle Tuxedo requests.
	<b>Busy Servers.</b> The total number of active servers currently busy handling Tuxedo requests.
	<b>Idle Servers.</b> The total number of active servers currently waiting to handle Tuxedo requests.
Server	<b>Number Queued.</b> The total number of messages which have been placed on the queue.
	<b>Requests/second.</b> The number of server requests handled per second.
	<b>Workload/second.</b> The workload is a weighted measure of the server requests. Some requests could have a different weight than others. By default, the workload is always 50 times the number of requests.


, continued

Monitor	Measurements
Workstation Handler (WSH)	<b>Bytes Received/sec.</b> The total number of bytes received by the workstation handler, per second.
	<b>Bytes Sent/sec.</b> The total number of bytes sent back to the clients by the workstation handler, per second.
	<b>Messages Received/sec.</b> The number of messages received by the workstation handler, per second.
	<b>Messages Sent/sec.</b> The number of messages sent back to the clients by the workstation handler, per second.
	<b>Number of Queue Blocks/sec.</b> The number of times the queue for the workstation handler blocked, per second. This gives an idea of how often the workstation handler was overloaded.

## IBM WebSphere MQ Graph

This graph shows the resource usage of IBM WebSphere MQ Server channel and queue performance counters as a function of the elapsed load test scenario time.


X-axis	Elapsed time since the start of the run.
Y-axis	The resource usage of the IBM WebSphere MQ Server channel and queue performance counters.
Note	To obtain data for this graph, you need to enable the IBM WebSphere MQ monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
See also	<a href="#">"Middleware Performance Graphs Overview" on page 1625</a> <a href="#">"IBM WebSphere MQ Counters" on page 1625</a>



## Tuxedo Resources Graph

This graph provides information about the server, load generator machine, workstation handler, and queue in a Tuxedo system.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The resource usage on the Tuxedo system.
<b>Note</b>	To obtain data for this graph, you need to enable the TUXEDO monitor (from the Controller) and select the default measurements you want to display, before running the scenario.
<b>See also</b>	<a href="#">"Middleware Performance Graphs Overview" on page 1625</a> <a href="#">"Tuxedo Resources Graph Measurements" on page 1627</a>



## Infrastructure Resources Graphs

### Infrastructure Resources Graphs Overview

LoadRunner's Infrastructure Resources monitor provides you with information about the performance of FTP, POP3, SMTP, IMAP, and DNS Vusers on the network client during load test scenario execution.


### Network Client Measurements

Measurement	Description
Pings per sec	Number of pings per second.
Data transfer bytes per sec	Number of data bytes transferred per second.
Data receive bytes per sec	Number of data bytes received per second.
Connections per sec	Number of connections per second.
Accept connections per sec	Number of connections accepted per seconds.
SSL Connections per sec	Number of SSL connections per second.
SSL Data transfer bytes per sec	Number of SSL data bytes transferred per second.
SSL Data receive bytes per sec	Number of SSL data bytes received per second.
SSL Accept connections per sec	Number of SSL connections accepted per seconds.

## Network Client Graph

This graph displays network client data points for FTP, POP3, SMTP, IMAP, and DNS Vusers during a load test scenario run.

X-axis	Elapsed time since the start of the run.
Y-axis	The resource value of the network client data points..
See also	<a href="#">"Infrastructure Resources Graphs Overview" on the previous page</a>




## Analysis Reports

### Understanding Analysis Reports

## Analyze Transaction Settings Dialog Box

This dialog box enables you to configure the Transaction Analysis Report to show correlations between the graph of the analyzed transaction and other graphs that you select.



<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• <b>Reports &gt; Analyze Transaction &gt; Settings</b></li><li>• <b>Tools &gt; Options &gt; Analyze Transaction Settings tab</b></li></ul>
<b>See also</b>	<a href="#">"Analyze Transactions Dialog Box" on the next page</a>


User interface elements are described below:

UI Element	Description
<b>Correlations</b>	Defines which graphs you want Analysis to match to the graph of the transaction you selected. Graphs where data is available appear in blue.

UI Element	Description
<b>Show correlations with at least x% match</b>	The positive or negative percentage correlation between the graph of the analyzed transaction and the graphs selected above. You can change the percentage by entering a value in the box. The default is 20%.
<b>Auto adjust time range to best fit</b>	Analysis adjusts the selected time range to focus on the SLA violations within and around that time period. This option only applies when the Transaction Analysis report is generated directly from the Summary report (from the <b>X Worst transactions</b> or <b>Scenario behavior over time</b> sections).
<b>Show correlations with insufficient data lines</b>	Displays correlations where one of the measurements contains less than 15 units of granularity.
<b>Errors</b>	Displays errors in the Transaction Analysis Report if selected.

## Analyze Transactions Dialog Box

You use the Analyze Transaction dialog box to define the criteria that will be used to analyze the selected transaction in the Transaction Analysis Report. You can analyze a transaction even if you have not defined an SLA.



To access	<p><b>Reports &gt; Analyze Transaction</b></p> <p><b>Summary Report &gt; right-click menu &gt; Add New Item &gt; Analyze Transaction</b></p> <p><b>Toolbar &gt;</b> </p> <p><b>Summary Report with no SLA &gt; Statistics Summary section &gt; Analyze Transaction tool link</b></p>
Note	Analysis data (for example, transactions) that has been excluded by the Summary Filter will not be available for analysis in the Transaction Analysis report.
See also	"Filtering and Sorting Graph Data" on page 1394


User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
Show time ranges based on box	Select one of the display options: <ul style="list-style-type: none"><li><b>Suggestions.</b> Lists all transactions and time ranges from the scenario run.</li><li><b>SLA Violations.</b> Lists only those transactions and time ranges where the transaction exceeded the SLA. This option does not appear if there were no transactions that exceeded the SLA.</li></ul>
Transaction	Select the transaction to analyze from the Transaction tree.
<Time Range>	Select the time range to analyze in one of the following ways: <ul style="list-style-type: none"><li>Select the time range from the Transaction tree.</li><li>Enter the time range in the <b>From</b> and <b>To</b> boxes above the graph.</li><li>Select the time range by dragging the bars on the graph.</li></ul>
<Display options>	Select one of the following: <ul style="list-style-type: none"><li><b>Running Vusers</b></li><li><b>Throughput</b></li><li><b>Hits per Second</b></li></ul> The option you select is displayed on the graph and will appear on the snapshot of the graph that appears on the Transaction Analysis Report. Note that your choice only affects the display of the graph and not the calculation for correlations.

UI Element	Description
<b>Settings</b>	Click <b>Settings</b> to define the Analyze Transaction settings in the <b>Analyze Transaction Settings</b> dialog box. For more information, see " <a href="#">"Analyze Transaction Settings Dialog Box" on page 1633</a> ".  <b>Note:</b> You can also define the Analyze Transaction settings in the <b>Analyze Transaction Settings</b> tab of the <b>Options</b> dialog box ( <b>Tools &gt; Options</b> ).
<b>Generate report</b>	The Transaction Analysis Report opens. Once the report has been created, you can access it at any time from the Session Explorer.

## New Report Dialog Box

This dialog box enables you to create a report based on the report template selected. You can adjust the report template settings to generate a report that corresponds to the required report layout.



<b>To access</b>	<b>Reports &gt; New Report</b>
<b>See also</b>	<a href="#">"Report Templates Dialog Box" on the next page</a>  <b>Note:</b> This dialog box and the Report Templates dialog box utilize the same components.

User interface elements are described below:

UI Element	Description
<b>Based on Template</b>	The template upon which to build the report. After you select a template, the corresponding settings of the report template appear.
<b>General tab</b>	For user interface details, see " <a href="#">Report Templates - General Tab</a> " on page 1639.
<b>Format tab</b>	For user interface details, see " <a href="#">Report Templates - Format Tab</a> " on page 1640.
<b>Content tab</b>	For user interface details, see " <a href="#">Report Templates - Content Tab</a> " on page 1642.
<b>Save As Template</b>	Prompts you for a template name that will be added to the report template list.
<b>Generate</b>	Generates the report according to your settings.

## Analysis Report Templates

### **Report Templates Overview**


You can use Report Templates to create and customize templates which are used when generating reports. Report templates can be used across similar scenario runs and saves time and effort on recreating reports each time.

Using the Report Templates dialog box, you can record document details, define the format of the report, and select the content items to include in the report and configure each content item accordingly.

A list of report templates is displayed in the **Templates** dialog box, under **Rich Reports**. Select this option if you want to generate the report in the load run session in word, excel, HTML or PDF format. For more information on templates, see "[Apply/Edit Template Dialog Box](#)" on page 1389.

### **Report Templates Dialog Box**

This dialog box enables you to add, modify, import, export, or duplicate a report template.



<b>To access</b>	<b>Reports &gt; Report Templates</b>
<b>See also</b>	<ul style="list-style-type: none"> <li>• <a href="#">"Report Templates Overview" on the previous page</a></li> <li>• <a href="#">"New Report Dialog Box" on page 1636</a></li> </ul> <p><b>Note:</b> This dialog box and the New Report dialog box utilize the same components.</p>

User interface elements are described below:

UI Element	Description
	<b>New.</b> Adds a new report template.
	<b>Delete.</b> Removes the selected template.
	<b>Import.</b> Imports a report template from an XML file.
	<b>Export.</b> Saves the selected template as an XML file.
	<b>Duplicate.</b> Creates a copy of the selected template.

UI Element	Description
<b>General tab</b>	For user interface details, see " <a href="#">Report Templates - General Tab</a> " below.
<b>Format tab</b>	For user interface details, see " <a href="#">Report Templates - Format Tab</a> " on the next page.
<b>Content tab</b>	For user interface details, see " <a href="#">Report Templates - Content Tab</a> " on page 1642.
<b>Generate Report button</b>	Generates the report according to your settings.

## Report Templates - General Tab

This tab enables you to record document details, such as title, author name and title and set global settings, such as Report Time Range and granularity.

The screenshot shows the 'General' tab of the Report Templates dialog box. It includes fields for recording document details (Title, Author) and setting global reporting parameters (Report Time Range, Granularity, Precision). A descriptive text box outlines the template's purpose and the metrics it generates.


<b>To Access</b>	<b>Reports &gt; New Report... &gt; General tab</b>  <b>or</b>  <b>Reports &gt; Report Templates... &gt; General tab</b>
<b>See also</b>	<ul style="list-style-type: none"><li><a href="#">"Report Templates Overview" on page 1637</a></li><li><a href="#">"New Report Dialog Box" on page 1636</a></li><li><a href="#">"Report Templates Dialog Box" on page 1637</a></li></ul>

User interface elements are described below:

UI Element	Description
<b>Title</b>	A description of the template.
<b>First Name</b>	The first name of the person to display on the report.
<b>Surname</b>	The last name of the person to display on the report.
<b>Job title</b>	The job title of the person to display on the report.
<b>Organization</b>	The name of the organization to display on the report.
<b>Description</b>	You can enter a description and include details of the report template.
<b>Report Time Range</b>	The default setting is Whole Scenario. Click  to set the start and end time range of the scenario run time to display on the report.
<b>Granularity</b>	Define granularity settings (in seconds).
<b>Precision</b>	The number of digits to appear after the decimal point in none graph content items.
<b>Include Think Time</b>	Include think time when processing the Analysis data. This data is then used when generating reports.
<b>Use Raw Result Time Zone</b>	When creating the report, use the time zone that was generated in the raw data results.

## ***Report Templates - Format Tab***

This tab enables you to define the format of report template.



<b>To access</b>	<b>Reports &gt; New Report... &gt; Format tab</b>  <b>or</b> <b>Reports &gt; Report Templates... &gt; Format tab</b>
<b>See also</b>	<ul style="list-style-type: none"><li>• "<a href="#">Report Templates Overview</a>" on page 1637</li><li>• "<a href="#">New Report Dialog Box</a>" on page 1636</li><li>• "<a href="#">Report Templates Dialog Box</a>" on page 1637</li></ul>


User interface elements are described below:

UI Element	Description
<b>General</b>	General options such as: <ul style="list-style-type: none"><li>• include a cover page</li><li>• include table of contents</li><li>• include company logo</li></ul>

UI Element	Description
<b>Page Header and Footer</b>	Header and footer options: <ul style="list-style-type: none"><li>• Font type, size and color</li><li>• Bold, italicize, or underline</li><li>• Right, center or left align</li><li>• You can add tags, such as date, name or organization.</li><li>• You can include required details such as page count, date, name, and so forth on the left, center or right column.</li></ul>
<b>Normal Font</b>	The type of font to use in the report template.
<b>Heading 1/2</b>	The style for your headings.
<b>Table</b>	Table format options: <ul style="list-style-type: none"><li>• Font type, size and color</li><li>• Background color</li><li>• Bold, italicize, or underline</li><li>• Right, center or left align</li></ul>

## **Report Templates - Content Tab**

This tab enables you to select the content items to include in the report and configure each item accordingly.



<b>To access</b>	<b>Reports &gt; New Report... &gt; Content tab</b> or <b>Reports &gt; Report Templates... &gt; Content tab</b>
<b>See also</b>	<ul style="list-style-type: none"><li>• "<a href="#">Report Templates Overview</a>" on page 1637</li><li>• "<a href="#">New Report Dialog Box</a>" on page 1636</li><li>• "<a href="#">Report Templates Dialog Box</a>" on page 1637</li></ul>

User interface elements are described below:

UI Element	Description
	<b>Add Content.</b> Opens the Add Content Items pane. Select one or more items from the grid and click <b>OK</b> .
	<b>Delete Content.</b> Removes the selected items from the Content Items pane.
	<b>Reorder.</b> Reorders the content items, determining how they will be shown in the report.
<b>Contents Item pane</b>	A list of the content items to be included in the report. <ul style="list-style-type: none"><li>• To add more items, click the Add Content button.</li><li>• To learn about a content item, select it and view the information in the Description pane beneath it.</li></ul>

UI Element	Description
<Configuration pane>	<p>Settings for the selected content item. The components and tabs in this pane vary, based on the selected content item.</p> <ul style="list-style-type: none"><li>• <b>Parameters tab.</b> Settings such as integer values for percentiles or number of elements.</li><li>• <b>Columns tab.</b> Allows you to select the columns to include in the report. To include a column, make sure it appears in the <b>Selected Columns</b> pane.</li><li>• <b>Filter tab.</b> Allows you to enter criteria for including a specific range of a measurement.</li><li>• <b>Text area.</b> A rich text box for enter free text, such as in a Placeholder Section or an Executive Summary.</li></ul>
<b>Generate Report</b>	Generates the report according to your settings.

## Analysis Report Types

### *Summary Report Overview*

The Summary report provides general information about load test scenario execution. This report is always available from the Session Explorer or as a tab in the Analysis window.

The Summary report lists statistics about the scenario run and provides links to the following graphs: Running Vusers, Throughput, Hits Per Second, HTTP Responses per Second, Transaction Summary, and Average Transaction Response Time.

The appearance of the Summary report and the information displayed, will vary depending on whether an SLA (Service Level Agreement) was defined.

An SLA defines goals for the scenario. LoadRunner measures these goals during the scenario run, and analyzes them in the Summary report. For more information on defining an SLA, see "[SLA Reports](#)" on page 1650

A Summary report is also provided for Cross Result graphs. For more information about Cross Result graphs, see "[Cross Result Graphs Overview](#)" on page 1433.

**Note:** You can save the Summary reports to an Excel file by selecting **View > Export Summary to Excel** or by clicking the **Export Summary to Excel** button on the toolbar.

### *Summary Report*

The Summary report provides general information about load test scenario execution. It lists statistics about the scenario run and provides links to the following graphs: Running Vusers,

Throughput, Hits Per Second, HTTP Responses per Second, Transaction Summary, and Average Transaction Response Time.

To access	Session Explorer > Reports > Summary Report
Important information	The Summary report for SAP Diagnostics, J2EE /.NET Diagnostics, and Siebel Diagnostics provides a usage chart that links to and displays each individual transaction's Web, application, and database layers, and provides the total usage time for each transaction.
Relevant tasks	You can save the Summary reports to an Excel file by selecting <b>View &gt; Export Summary to Excel</b> or by clicking  on the toolbar.
See also	<p>The Summary reports for the various diagnostics environments are discussed in detail in the following sections:</p> <p><a href="#">"SAP Diagnostics Summary Report" on page 1705</a> <a href="#">J2EE &amp; .NET Diagnostics Graphs Summary Report</a> <a href="#">"Siebel Diagnostics Graphs Summary Report" on page 1673</a></p>

## Summary Report with No SLA

User interface elements are described below:

UI Element	Description
Scenario Details	Shows the basic details of the load test scenario being analyzed.
Statistics Summary	This section shows a breakdown of the transaction statistics and also provides links to the following: <ul style="list-style-type: none"><li>The SLA configuration wizard. For more information on defining an SLA, see <a href="#">"SLA Reports" on page 1650</a></li><li>The Analyze Transaction tool. For more information on analyzing transactions, see <a href="#">"Analyze Transactions Dialog Box" on page 1634</a></li></ul>

, continued

UI Element	Description
<b>Transaction Summary</b>	<p>This section displays a table containing the load test scenario's diagnostics data. Included in this data is a percentile column (x Percent). This column indicates the maximum response time for that percentage of transactions performed during the run.</p> <p><b>Note:</b> You can change the value in the percentile column in one of the following ways:</p> <ul style="list-style-type: none"><li>Open the Options dialog box (<b>Tools &gt; Options</b>). Click the <b>General</b> tab and in the Summary Report section enter the desired percentile in the Transaction Percentile box.</li><li>Select <b>View &gt; Summary Filter</b> or click  on the toolbar. The Analysis Summary Filter dialog box opens. In the Additional Settings area enter desired percentile.</li></ul>
<b>HTTP Responses Summary</b>	<p>This section shows the number of HTTP status codes returned from the Web server during the load test scenario, grouped by status code.</p> <p><b>Note:</b> There are additional Diagnostics sections that may appear at the end of the Summary report, depending on the configuration of your system.</p>

## Summary Report with SLA

User interface elements are described below:

UI Element	Description
<b>Scenario details</b>	This section shows the basic details of the load test scenario being analyzed.
<b>Statistics Summary</b>	This section shows a breakdown of the transaction statistics.

, continued

UI Element	Description
X Worst Transactions	<p>The X Worst Transactions table shows the worst transactions in terms of how often the transactions exceeded the SLA boundary during the run, and by how much. Click <a href="#">here</a> to see an example of the 5 Worst transactions section of the summary report.</p> <p><b>Note:</b> You choose how many transactions are displayed in this table in the Summary Report section on the General tab of the options dialog box. Open the dialog box (<b>Tools &gt; Options</b>) and enter the number of transactions to display. The default is <b>5</b>.</p> <p>You expand a transaction to get more information. When expanded, the following information appears for each transaction:</p> <p><b>Failure Ratio</b></p> <ul style="list-style-type: none"><li>▪ The percentage of time intervals where the transaction exceeded the SLA. You can see this graphically in the Scenario Behavior Over Time section below.</li></ul> <p><b>Failure Value</b></p> <ul style="list-style-type: none"><li>▪ The average percentage by which the transaction exceeded the SLA over the whole run.</li></ul> <p><b>Avg exceeding ratio</b></p> <ul style="list-style-type: none"><li>▪ The average percentage by which the transaction exceeded the SLA over a specific time interval. For example, in the first time interval in the screenshot above, the figure is 4.25%. This means that during that time interval, the transaction may have exceeded the SLA boundary several times, each time by a different percentage margin, the average percentage being 4.25%.</li></ul> <p><b>Max exceeding ratio</b></p> <ul style="list-style-type: none"><li>▪ The highest percentage by which the transaction exceeded the SLA over a specific time interval. For example, using the same time interval as above, the transaction may have exceeded the SLA several times, each time by a different percentage margin. The highest percentage being 7.39%</li></ul> <p>Analysis allows you to analyze a specific transaction in more detail. You open the Analyze Transaction tool from this section by clicking the <b>Analyze Transaction</b> button. For more information on Transaction Analysis Reports, see "<a href="#">Analyze Transactions Dialog Box</a>" on page 1634.</p>

, continued

UI Element	Description
<b>Scenario Behavior Over Time</b>	<p>This section shows how each transaction performed in terms of the SLA over time intervals. The green squares show time intervals where the transaction performed within the SLA boundary. Red squares show time intervals where the transaction failed and gray squares show where no relevant SLA was defined.</p> <p><b>Note:</b> The time intervals displayed in the <b>Scenario Behavior Over Time</b> section may vary for each interval. The time interval set in the tracking period of the SLA is only the minimum time interval that will be displayed.</p> <p>It is only the display that varies. The SLA is still determined over the time interval you choose in the <b>Advanced Settings</b> section.</p> <p>Analysis allows you to analyze a specific transaction in more detail. You open the Analyze Transaction tool from the <b>Scenario Behavior Over Time</b> section in one of the following ways:</p> <ul style="list-style-type: none"> <li>• Select the transaction to analyze from the list and enter the time interval in the <b>From</b> and <b>To</b> boxes. Then click <b>Analyze Transaction</b>.</li> <li>• Drag the mouse over the desired transaction and time range to analyze. Then click <b>Analyze Transaction</b>.</li> </ul> <p>For more information on Transaction Analysis Reports, see "<a href="#">Analyze Transactions Dialog Box</a>" on page 1634.</p>
<b>Transaction Summary</b>	<p>This section displays a table containing the load test scenario's diagnostics data. Included in this data is a percentile column (x Percent). This column indicates the maximum response time for that percentage of transactions performed during the run. For example, in the table below, the value in the 88 Percent column for <b>browse special books</b> is 8.072. This means that the response time for 88% of the <b>browse special books</b> transactions was less than 8.072 seconds. Click <a href="#">here</a> to see an example of a Transaction Summary.</p> <p><b>Note:</b> You can change the value in the percentile column in the Summary Report section of the General tab of the Options dialog box. Open the dialog box (<b>Tools &gt; Options</b>) and enter the desired percentage.</p> <p>Alternatively, you can also change the value in the Summary Filter (<b>View &gt; Summary Filter</b>).</p>
<b>HTTP Responses Summary</b>	<p>This section shows the number of HTTP status codes returned from the Web server during the load test scenario, grouped by status code.</p> <p><b>Note:</b> There are additional Diagnostics sections that may appear at the end of the Summary report, depending on the configuration of your system.</p>


## Summary reports for Cross Result Graphs

User interface elements are described below:

UI Element	Description
<graphs>	<p>Displays summary information for the scenarios that you are comparing. The information is displayed in a way that enables you to compare data from the different scenarios. Includes the same type of information as the regular Summary report except for the following:</p> <ul style="list-style-type: none"><li>• SLA information</li><li>• Diagnostics information</li><li>• Scenario behavior over time</li></ul>

## HTML Report

Analysis enables you to create HTML reports for your load test scenario run. It creates a separate page for each one of the open graphs and reports.



<b>To access</b>	Use one of the following: <ul style="list-style-type: none"><li>• <b>Reports &gt; HTML Report</b></li><li>• <b>Toolbar &gt;</b> </li></ul>
<b>Relevant tasks</b>	<ul style="list-style-type: none"><li>• Open all graphs that you want to include in the report.</li><li>• Specify a path and file name for the HTML report and click <b>Save</b>. Analysis saves a Summary report which has the same name as the file in the selected folder. The rest of the graphs are saved in a folder with the same name as the Summary report's file name. When you create an HTML report, Analysis opens your default browser and displays the Summary report.</li><li>• To copy the HTML reports to another location, be sure to copy the filename and the folder with the same name. For example, if you named your HTML report test1, copy test1.html and the folder test1 to the desired location</li></ul>

User interface elements are described below:

UI Element	Description
<b>&lt;Graphs&gt; menu left frame</b>	Click the graph link to view an HTML report for that graph.
	You can view an Excel file containing the graph data, by clicking the <b>Graph data in Excel format</b> button on the relevant graph page.

## SLA Reports

An SLA (Service Level Agreement) defines goals for the load test scenario. LoadRunner measures these goals during the scenario run and analyzes them in the Summary report. The SLA Report shows the succeeded or failed status of all SLAs that were defined for the scenario run.

**Note:** Analysis data (for example, transactions) that has been excluded by the Summary Filter will not be available for analysis in the SLA report.

<b>To access</b>	You create the SLA Report in one of the following ways:  <b>Reports &gt; Analyze SLA</b>  <b>Right-click the Summary pane &gt; Add New Item &gt; Analyze SLA</b>  <b>Summary Report &gt;</b> 
<b>Relevant tasks</b>	<a href="#">"Defining Service Level Agreements " on page 1437</a>

User interface elements are described below:

UI Element	Description
Display of SLA statuses	<p><b>SLA Status per goal definition</b></p> <ul style="list-style-type: none"><li>▪ Where the SLA was defined over the whole run, the report displays a single SLA status for each goal definition.</li></ul> <p><b>SLA status for each transaction per time interval</b></p> <ul style="list-style-type: none"><li>▪ Where the SLA was defined per time interval within the run, the report displays the status of the SLA for each transaction per time interval. The green squares show time intervals where the transaction performed within the SLA boundary. Red squares where the transaction failed and gray squares show where no relevant SLA was defined.</li></ul> <p><b>SLA goal definitions</b></p> <ul style="list-style-type: none"><li>▪ Where the SLA was defined per time interval within the run, a further section appears detailing the goal definitions for the SLA.</li></ul>

## Transaction Analysis Report

This report enables you to individually examine each of the transactions from the load test scenario run.

To access	Reports > Analyze Transaction > Generate Report button
-----------	--------------------------------------------------------

User interface elements are described below:

UI Element	Description
Observations	<p>This section shows both positive and negative correlations between the graph of the transaction being analyzed, and other graphs based on the settings you chose in the Analyze Transaction Dialog Box. When two graphs are correlated, it means that their behavior matches each other by a certain percentage.</p> <p> To view the correlating graph, select one of the results and then click the View Graph icon at the bottom of the section. The graph comparison opens.</p> <p> You can return to the Transaction Analysis Report from the graph comparison at anytime by clicking the Back to &lt;transaction name&gt; icon on the toolbar.</p> <p><b>Note:</b> The correlations are automatically calculated according to a default ratio of 20%. You can adjust this ratio by clicking the arrows next to the percentage. Then click <b>Recalculate</b>.</p>

UI Element	Description
<b>Errors</b>	This section is divided into two sub-sections. <ul style="list-style-type: none"><li>• <b>Application Under Test errors.</b> Shows errors that occurred during the transaction that were direct results of Vuser activity.</li><li>• <b>All errors.</b> Shows Application Under Test errors as well as errors that were not related to Vuser activity, and which affected your system and not the application under test.</li></ul>
<b>Observation Settings</b>	This section displays a summary of the settings that were selected in the Advanced Settings section of the Analyze Transaction dialog box.
<b>Graph</b>	The Graph section displays a snapshot of selected transaction and time range for analysis merged with the display option you selected (Running Vusers, Throughput, or Hits per Second). Note that it is only a snapshot and can not be manipulated like normal graphs.

## Analysis Reports Overview



After running a load test scenario, you can view reports that summarize your system's performance. Analysis provides the following reporting tools:

- "[Summary Report](#)" on page 1644
- "[SLA Reports](#)" on page 1650
- "[Transaction Analysis Report](#)" on the previous page
- "[HTML Report](#)" on page 1649

The Summary report provides general information about the scenario run. You can access the Summary report at any time from the Session Explorer.

The SLA report provides an overview of the defined SLAs (Service Level Agreements) with succeeded or failed status.

The Transaction Analysis report provides a detailed analysis of a specific transaction over a specific time period.

You can instruct Analysis to create an HTML report. The HTML report contains a page for each open graph, the Summary report, the SLA report, and the Transaction Analysis report.

Transaction reports provide performance information about the transactions defined within the Vuser scripts. These reports give you a statistical breakdown of your results and allow you to print and export the data.

**Note:** SLA reports and Transaction Analysis reports are not available when generating Cross Result graphs. For more information on Cross Result graphs, see "[Cross Result and Merged Graphs](#)" on page 1432.

## Importing External Data

### Import Data Tool Overview

The LoadRunner Analysis Import Data tool enables you to import and integrate non-HP data into a LoadRunner Analysis session. After the import procedure, you can view the data files as graphs within the session, using all the capabilities of the Analysis tool.

Suppose an NT Performance Monitor runs on a server and measures its behavior. Following a LoadRunner scenario on the server, you can retrieve the results of the Performance Monitor, and integrate the data into LoadRunner's results. This enables you to correlate trends and relationships between the two sets of data: LoadRunner's and the Performance Monitor's.


In this case, the results of the NT Performance Monitor are saved as a **.csv** file. You launch the Import Data tool, direct it to the **.csv** file, and specify its format. LoadRunner reads the file and integrates the results into its own Analysis session.

For a list of data formats that are supported, see "[Supported File Types](#)" on page 1655. To define your own custom data files, see "[How to Define Custom File Formats](#)" on page 1655.

### How to Use the Import Data Tool

This task describes how to import data files to integrate into your analysis session.

1. Choose **Tools > External Monitors > Import Data**. The Import Data dialog box opens.



2. Select the format of the external data file from the **File format** list box.
  3. Click **Add File**. In the **Select File to Import** dialog box that opens, the **Files of type** list box shows the type chosen in step 2.
  4. Set other file format options, as described in "[Import Data Dialog Box](#)" on page 1659. You must enter a machine name.
  5. To specify character separators and symbols, click **Advanced**. For more information, see "[Advanced Settings Dialog Box \(Import Data Dialog Box\)](#)" on page 1657.
  6. Click **Next**. The Import Data dialog box opens.
  7. Select the type of monitor that generated the external data file. If your monitor type does not exist, you can add it, as described in [How to Customize Monitor Types for Import](#).
- When opening a new graph, you will see your monitor added to the list of available graphs under this particular category. (See "[Open a New Graph Dialog Box](#)" on page 1359.)
8. Click **Finish**. LoadRunner Analysis imports the data file or files, and refreshes all graphs currently displayed in the session.

**Note:** When importing data into a scenario with two or more cross results, the imported data will be integrated into the last set of results listed in the **File > Cross with Result** dialog box. For more information, see "[How to Generate Merged Graphs](#)" on page 1436.

## How to Define Custom File Formats

This task describes how to define a custom format, if the file format of your import file is not supported.

If the file format of your import file is not supported, you can define a custom format.

1. Choose **Tools > External Monitors > Import Data**. The Import Data dialog box opens.
2. From the **File Format** list, select **<Custom File Format>**. The Enter New Format Name dialog box opens.
3. Enter a name for the new format (in this case, `my_monitor_format`).
4. Click **OK**. The Define External Format dialog box opens.
5. Specify the mandatory and optional data, as described in "[Define External Format Dialog Box](#)" on page 1658.
6. Click **Save**.

## Supported File Types

The following file types are supported:

### NT Performance Monitor (.csv)

Default file type of NT Performance monitor, in comma separated value (CSV) format.

For example:

```
Reported on \\WINTER
Date: 10/23/01
Time: 10:08:39 AM
Data: Current Activity
Interval: 1.000 seconds

..% Privileged Time,% Processor Time,% User Time,
.,0,0,0.

:::::,Processor,Processor,Processor,
Date,Time,\\WINTER,\\WINTER,\\WINTER,
10/23/01,10:07:00 AM , 0.998, 1.174, 0.000,
10/23/01,10:07:01 AM , 0.000, 0.275, 0.000,
```

### Windows 2000 Performance Monitor (.csv)

Default file type of Windows 2000 Performance monitor, but incompatible with NT Performance monitor. In comma separated value (CSV) format.

For example:

```
"(PDH-CSV_4.0)", "\\MACRON\Processor(_Total)\% Processor Time", "\\MACRON\Processor(_Total)\% User Time", "\\MACRON\Processor(_Total)\Interrupts/sec", "\\MACRON\System\File Control Bytes/sec"  
"10/29/2001  
13:09:33.746", "99.999148401465547", "0.0021716772078191897", "997.21487008127474", "488.53479318892;  
"10/29/2001  
13:09:48.747", "18.157543391188248", "8.4112149532710276", "1116.5859176246415", "9843.2933303122791;  
"10/29/2001  
13:10:03.749", "5.941255006675572", "1.5353805073431241", "1100.9651204860379", "623.18277489319848"
```

## Standard Comma Separated File (.csv)

This file type has the following format:

Date,Time,Measurement\_1,Measurement\_2, ...

where fields are comma separated and first row contains column titles.

The following example from a standard CSV file shows 3 measurements: an interrupt rate, a file IO rate and a CPU usage. The first row shows an interrupt rate of 1122.19 and an IO rate of 4.18:

```
date, time, interrupt rate, File IO rate, CPU bust percent  
25/05/01,10:09:01,1122.19,4.18,1.59  
25/05/01,10:10:01,1123.7,6.43,1.42
```

## Master-Detail Comma Separated File (.csv)

This file type is identical to Standard Comma Separated Files except for an additional **Master** column which specifies that row's particular breakdown of a more general measurement. For example, a Standard CSV file may contain data points of a machine's total CPU usage at a given moment:

Date,Time,CPU\_Usage

However, if the total CPU usage can be further broken up into CPU time per-process, then a Master-Detail CSV file can be created with an extra column **ProcessName**, containing the name of a process.

Each row contains the measurement of a specific process's CPU usage only. The format will be the following:

Date,Time,ProcessName,CPU\_Usage

as in the following example:

```
date, time,process name, CPU used, elapsed time used  
25/05/01,10:06:01,edaSend,0.1,47981.36  
25/05/01,10:06:01,PDS,0,47981.17
```

## Microsoft Excel File (.xls)

Created by the Microsoft Excel application. The first row contains column titles.

	A	B	C	D	E
1	date	time	interrupt rate	File IO rate	CPU bust percent
2	25/05/01	10:09:01	1122.19	4.18	1.59
3	25/05/01	10:10:01	1123.7	6.43	1.42
4	25/05/01	10:11:01	1103.62	5.33	1.17
5	25/05/01	10:12:01	1118.89	12.18	2.37
6	25/05/01	10:13:01	1116.89	19.85	3.87
7	25/05/01	10:14:01	1128.12	19.9	4.15
8	25/05/01	10:15:01	1151.98	20.82	4.25
9	25/05/01	10:16:01	1110.1	4.83	1.34


### Master-Detail Microsoft Excel file (.xls)

Created by Microsoft's Excel application. The first row contains column titles. It contains an extra **Master** column.

	A	B	C	D	E
1	date	time	process name	CPU used	elapsed time used
2	25/05/01	10:06:01	edaSend	0.1	47981.36
3	25/05/01	10:06:01	PDS	0	47981.17
4					

## Advanced Settings Dialog Box (Import Data Dialog Box)

This dialog box enables you to define the data format of the imported file to settings other than of the regional configuration.



To access	Tools > External Monitors > Import Data > Advanced
-----------	----------------------------------------------------

User interface elements are described below:

UI Element	Description
<b>Use local settings</b>	Keep default settings of the regional configuration. Disables the <b>Custom Settings</b> area of the dialog box.
<b>Use custom settings</b>	Define your own settings. Enables the <b>Custom Settings</b> area of the dialog box. <ul style="list-style-type: none"><li>• <b>Date Separator.</b> Enter a custom symbol, for example, the slash ('/') character in 11/10/02</li><li>• <b>Time Separator.</b> Enter a custom symbol, for example, the colon `:` character in 9:54:19</li><li>• <b>Decimal symbol.</b> Enter a custom symbol, for example, the `.` character in the number 2.5</li><li>• <b>AM symbol.</b> Enter a custom symbol for the hours between midnight and noon.</li><li>• <b>PM symbol.</b> Enter a custom symbol for the hours between noon and midnight.</li></ul>

## Define External Format Dialog Box

This dialog box enables you to define a new file format for external data files not supported by Analysis.

The Define External Format dialog box is divided into mandatory and optional information.

To access	Tools > External Monitors > Import data > File Format > <Custom File Format>
Relevant tasks	<a href="#">"How to Define Custom File Formats" on page 1655</a>

### Mandatory tab

User interface elements are described below:

UI Element	Description
<b>Date Column Number</b>	Enter the column that contains the date. If there is a master column (see <a href="#">"Supported File Types" on page 1655</a> ), specify its number.
<b>Time Column Number</b>	Enter the column that contains the time.

UI Element	Description
<b>Use Master Column</b>	Select this if the data file contains a master column. A master column specifies the row's particular breakdown of a more general measurement.
<b>File Extension</b>	Enter the file suffix.
<b>Field Separator</b>	Enter the character that separates a field in a row from its neighbor. To select a field separator character, click <b>Browse</b> and select a character from the define Field Separator dialog box.


## Optional tab

User interface elements are described below:

UI Element	Description
<b>Date Format</b>	Specify the format of the date in the imported data file. For example, for European dates with a 4 digit year, choose <b>DD/MM/YYYY</b> .
<b>Time Zone</b>	Select the time zone where the external data file was recorded. LoadRunner Analysis aligns the times in the file with local time zone settings to match LoadRunner results. (LoadRunner does not alter the file itself).
<b>Machine Name</b>	Specify the machine name the monitor runs on. This associates the machine name with the measurement.
<b>Exclude Columns</b>	Indicate which columns are to be excluded from the data import, such as columns containing descriptive comments. When there is more than one column to be excluded, specify the columns in a comma-separated list. For example, 1,3,8.
<b>Convert file from UNIX to DOS format</b>	Monitors often run on UNIX machines. Check this option to convert data files to Windows format. A carriage return (Ascii character 13) is appended to all line feed characters (Ascii character 10) in the UNIX file.
<b>Skip the first <input type="text"/> lines</b>	Specify the number of lines at the start of the file to ignore before reading in data. Typically, the first few lines in a file contain headings and sub-headings.

## Import Data Dialog Box

This dialog box enables you to import and integrate non-HP data files into Analysis session.



To access **Tools > External Monitors > Import Data**

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<b>Import data from the following files</b>	Displays the files that you selected for import.
<b>Add file</b>	Select an external data file to import. A dialog box opens to enable you to select files.
<b>Remove file</b>	Delete an external data file from the list.
<b>Open File</b>	Open an external data file using the associated application.
<b>File Format</b>	Set the file format options. <ul style="list-style-type: none"><li>• <b>File Format.</b> Choose the format of the external data file. For an explanation of available formats, see "<a href="#">Supported File Types</a>" on page 1655.</li><li>• <b>Date Format.</b> Specify the format of the date in the imported data file. For example, for European dates with a 4 digit year, choose <b>DD/MM/YYYY</b>.</li></ul>

UI Element	Description
<b>Time Zone</b>	Select the time zone where the external data file was recorded. LoadRunner Analysis compensates for the various international time zones and aligns the times in the file with local time zone settings in order to match LoadRunner results. If the times in the imported file are erroneous by a constant offset, you can synchronize the time.
<b>&lt;Synchronize with scenario start time&gt;</b>	Time Zone also contains the option <b>&lt;Synchronize with scenario start time&gt;</b> . Choose this to align the earliest measurement found in the data file to the start time of the LoadRunner scenario.
<b>Machine Name</b>	Specify the machine name the monitor runs on. This associates the machine name with the measurement. For example, a file IO rate on the machine fender will be named File IO Rate:fender. This enables you to apply Graph settings by the machine name. For more information, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394.
<b>Advanced</b>	For more information, see " <a href="#">Advanced Settings Dialog Box (Import Data Dialog Box)</a> " on page 1657.
<b>Truncate imported data to 150% of scenario run time</b>	In certain cases, the external monitor may have collected data over a time period that was larger than the actual load test. This option deletes data that was collected while the load test was not running, limiting the data collection period to 150% of the load testing period.


## Siebel Diagnostics Graphs

### Siebel Diagnostics Graphs Overview

Siebel Diagnostics graphs enable you to trace, time, and troubleshoot individual transactions through Web, application, and database servers.

To analyze where problems are occurring, you correlate the data in the Siebel Diagnostics graphs with data in the Transaction Response Time graphs.

You begin analyzing these graphs with the transaction graphs that display the average transaction response time during each second of the load test scenario run. For example, the following Average Transaction Response Time graph demonstrates that the average transaction response time for the **Action\_Transaction** transaction was high.



Using the Siebel Diagnostics graphs, you can pinpoint the cause of the delay in response time for this transaction.

Alternatively, you can use the Summary Report to view individual transactions broken down into Web, application, and database layers, and the total usage time for each transaction. For more information, see ["Siebel Diagnostics Graphs Summary Report" on page 1673](#).

**Note:** A measurement that is broken down in the Average Transaction Response Time graph will be different from the same measurement broken down in the Siebel Diagnostics graph. This is because the Average Transaction Response Time graph displays the average transaction response time, whereas the Siebel Diagnostics graph displays the average time per transaction event (sum of Siebel Area response time).

## How to Enable Siebel Diagnostics

To generate Siebel diagnostics data, you must first install the ERP/CRM Mediator (Mediator). For information on installing the Mediator, refer to the *HP LoadRunner Installation Guide*.

The Mediator is used to gather and correlate offline diagnostics data from the Siebel server. The Mediator processes the diagnostics data, and then passes it to the Controller.


**Note:** The Mediator must reside in the same LAN as the Siebel server.

To obtain diagnostics data for these graphs, you need to set up the Siebel Diagnostics module before running the scenario, and specify the sampling percentage of diagnostics data to include in the diagnostics graphs. For more information on configuring Siebel Diagnostics, refer to the *HP LoadRunner Controller User Guide*.

- The settings that you configure are per scenario. All scripts in the scenario will run under the same diagnostics configuration.
- To ensure that valid diagnostics data is generated, manually define the transactions in the Vuser script rather than using automatic transactions. Make sure to disable the following options in the run-time settings **General : Miscellaneous** node: **Define each action as a transaction** and **Define each step as a transaction**.

## Call Stack Statistics Window

This window enables you to view which components called the selected component.




<b>To access</b>	Analysis window > <Siebel> graph > right click sub-area and select <b>Siebel Diagnostics &gt; Show Sub-Area Call Stack Statistics</b>
<b>See also</b>	<a href="#">"Siebel Diagnostics Graphs Overview" on page 1661</a>

User interface elements are described below:

UI Element	Description
<b>Measurement</b>	Name of the sub-area, displayed as <b>AreaName:SubAreaName</b> . In the case of a database call, query information is also displayed. The percent shown indicates the percentage of calls to this component from its child.
<b>% of Root Sub-Area</b>	Displays the percentage of sub-area time in relation the total root sub-area time.
<b>No. of Calls to Root</b>	Displays the amount of times this transaction or sub-area was executed.
<b>Avg Time Spent in Root</b>	Time spent in root is the time that the sub-area spent in the root sub-area//transaction.  Average Time Spent in Root time is the total time spent in the root divided by the number of instances of the sub-area.
<b>STD Time Spent in Root</b>	The standard deviation time spent in the root.
<b>Min Time Spent in Root</b>	The minimum time spent in the root.
<b>Max Time Spent in Root</b>	The maximum time spent in the root.
<b>% of Called</b>	Displays the percentage of sub-area time in relation the child sub-area time.
<b>Total Time Spent in Root</b>	Displays the total sub-area execution time, including the child execution time.
	<b>Expand All.</b> Expands the entire tree.
	<b>Collapse All.</b> Collapses the entire tree.
	<b>Expand Worst Path.</b> Expands only the parts of the path on the critical path.
<b>Save to XML File</b>	Saves the tree data to an XML file.
<b>Properties</b>	<b>Properties</b> Area. Displays the full properties of the selected sub-area.
<b>SQL Query</b>	<b>SQL Query.</b> Displays the SQL query for the selected sub-area (For Database only).

## Chain of Calls Window

This window enables you to view the components that the selected transaction or sub-area called. The following figure shows all the calls in the critical path of the parent **Action\_Transaction** server-side transaction are displayed.



To access	Use one of the following: <ul style="list-style-type: none"><li>To view transaction call chains - right click a component and select <b>Siebel Diagnostics &gt; Show Chain of Calls</b></li><li>To view sub-area statistics - right click sub-area and select <b>Show Sub-Area Chain of Calls</b></li></ul>
Note	Each red node signifies the most time consuming child to its parent.

User interface elements are described below:

UI Element	Description
	<b>Switch to Sub-Area Chain of Calls.</b> When the sub-area call stack statistics data is displayed, this displays the sub-area chain of calls data (only if the root is a sub-area).
	<b>Switch to Sub-Area Call Stack Statistics.</b> When the sub-area chain of calls data is displayed, this displays the sub-area call stack statistics data (only if the root is a sub-area).


UI Element	Description
	<b>Show Sub-Area Chain of Calls.</b> Displays the Sub-Area Chain of Calls window.
	<b>Show Sub-Area Call Stack Statistics.</b> Displays the Sub-Area Call Stack Statistics window.
	<b>Properties.</b> Hides or displays the properties area (lower pane).
	<b>Columns.</b> Enables you to select the columns shown in the Calls window. To display additional fields, drag them to the desired location in the Calls window. To remove fields, drag them from the Calls window back to the Columns chooser.
<b>Measurement</b>	Name of the sub-area, displayed as <b>AreaName:SubAreaName</b> . In the case of a database call, query information is also displayed. The percent shown indicates the percentage of calls to this component from its parent.
<b>% of Transaction/ Root Sub-Area</b>	Displays the percentage of sub-area time in relation the total transaction/root sub-area time.
<b>No of Calls</b>	Displays the amount of times this transaction or sub-area was executed.
<b>Avg Response Time</b>	Response time is the time from the beginning of execution until the end. Average response time is the total response time divided by the number of instances of the area/sub-area.
<b>STD Response Time</b>	The standard deviation response time.
<b>Min Response Time</b>	The minimum response time.
<b>Max Response Time</b>	The maximum response time.
<b>% of Caller</b>	Displays the percentage of sub-area time in relation the parent sub-area time.
<b>Total time</b>	Displays the total sub-area execution time, including the child execution time.

## Siebel Area Average Response Time Graph

This graph displays the average response time for the server side areas, computed as the total area response time divided by the number of area calls.

<b>Purpose</b>	For example, if an area was executed twice by one instance of transaction A, and once by another instance of the same transaction, and it took three seconds for each execution, then the average response time is 9/3, or 3 seconds. The area time does not include calls made from the area to other areas.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) per area.
<b>Breakdown options</b>	For breakdown options, see " <a href="#">Siebel Breakdown Levels</a> " on page 1669.
<b>Tips</b>	<p>You can filter the Siebel graphs by the following fields:</p> <ul style="list-style-type: none"><li>• <b>Transaction Name.</b> Shows data for the specified transaction.</li><li>• <b>Scenario Elapsed Time.</b> Shows data for transactions that ended during the specified time.</li></ul> <p>For more information on filtering, see "<a href="#">Filtering and Sorting Graph Data</a>" on page 1394.</p>
<b>See also</b>	<a href="#">"Siebel Breakdown Levels"</a> on page 1669

### Example



## Siebel Area Call Count Graph

This graph displays the number of times that each Siebel area is called.


<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	The call count.
<b>Breakdown options</b>	For breakdown options, see " <a href="#">Siebel Breakdown Levels</a> " on the next page.
<b>Tips</b>	<p>You can filter the Siebel graphs by the following fields:</p> <ul style="list-style-type: none"><li>• <b>Transaction Name.</b> Shows data for the specified transaction.</li><li>• <b>Scenario Elapsed Time.</b> Shows data for transactions that ended during the specified time.</li></ul> <p>For more information on filtering, see "<a href="#">Filtering and Sorting Graph Data</a>" on <a href="#">page 1394</a>.</p>
<b>See also</b>	<a href="#">"Siebel Diagnostics Graphs Overview"</a> on page 1661

## Siebel Area Total Response Time Graph

This graph displays the total response time of each Siebel area.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) per area.
<b>Breakdown options</b>	For breakdown options, see " <a href="#">Siebel Breakdown Levels</a> " on the next page.
<b>Tips</b>	<p>You can filter the Siebel graphs by the following fields:</p> <ul style="list-style-type: none"><li>• <b>Transaction Name.</b> Shows data for the specified transaction.</li><li>• <b>Scenario Elapsed Time.</b> Shows data for transactions that ended during the specified time.</li></ul> <p>For more information on filtering, see "<a href="#">Filtering and Sorting Graph Data</a>" on <a href="#">page 1394</a>.</p>
<b>See also</b>	<a href="#">"Siebel Diagnostics Graphs Overview"</a> on page 1661

### Example






## Siebel Breakdown Levels



You can break down Siebel layers into areas, sub-areas, servers, and scripts to enable you to pinpoint the exact location where time is consumed.

<b>To access</b>	Use one of the following to access breakdown options: <ul style="list-style-type: none"><li>• &lt;<b>Siebel Diagnostics Graphs</b>&gt; &gt; View &gt; <b>Siebel Diagnostics</b></li><li>• &lt;<b>Siebel Diagnostics Graphs</b>&gt; &gt; select transaction &gt; short-cut menu &gt; <b>Siebel Diagnostics</b></li></ul> See toolbar options for each breakdown level.
<b>Important Information</b>	The breakdown menu options and buttons are not displayed until an element (transaction, layer, area, sub-area) is selected.
<b>See also</b>	<a href="#">"Siebel Diagnostics Graphs Overview" on page 1661</a>

Siebel Breakdown Levels are described below:

<b>Transaction Level</b>	<p>The following figure displays the top level Average Transaction Response Time graph. The graph displays several transactions.</p>  <p>This line graph shows Average Response Time (seconds) on the Y-axis (0 to 130) against Elapsed scenario time mm:ss on the X-axis (00:00 to 07:30). Multiple transactions are plotted with distinct markers and colors. A prominent purple line with diamond markers starts at ~95s, remains flat until ~06:30, then rises sharply to ~130s by 07:30. Other lines include orange diamonds (Create_Sales_Initial), green diamonds (close windows), blue diamonds (Create_Sales_Initial_2), red diamonds (Create_Outbound_Delivery), and various smaller lines for other transactions like Create_Standard_Overview and Create_Standard_Schedule_Line_Data.</p> <table border="1"> <thead> <tr> <th>Transaction</th> <th>Marker</th> <th>Color</th> </tr> </thead> <tbody> <tr><td>Action_Transaction</td><td>Diamond</td><td>Purple</td></tr> <tr><td>Create_Outbound_Delivery</td><td>Diamond</td><td>Red</td></tr> <tr><td>Create_Sales_Initial_2</td><td>Diamond</td><td>Blue</td></tr> <tr><td>Create_Standard_ItemData</td><td>Diamond</td><td>Orange</td></tr> <tr><td>Create_Standard_Overview_2</td><td>Diamond</td><td>Yellow</td></tr> <tr><td>close windows</td><td>Diamond</td><td>Green</td></tr> <tr><td>Create_Sales_Initial</td><td>Diamond</td><td>Orange</td></tr> <tr><td>Create_Sales_Overview</td><td>Diamond</td><td>Yellow</td></tr> <tr><td>Create_Standard_Overview</td><td>Diamond</td><td>Orange</td></tr> <tr><td>Create_Standard_Schedule_Line_Data</td><td>Diamond</td><td>Yellow</td></tr> </tbody> </table>	Transaction	Marker	Color	Action_Transaction	Diamond	Purple	Create_Outbound_Delivery	Diamond	Red	Create_Sales_Initial_2	Diamond	Blue	Create_Standard_ItemData	Diamond	Orange	Create_Standard_Overview_2	Diamond	Yellow	close windows	Diamond	Green	Create_Sales_Initial	Diamond	Orange	Create_Sales_Overview	Diamond	Yellow	Create_Standard_Overview	Diamond	Orange	Create_Standard_Schedule_Line_Data	Diamond	Yellow
Transaction	Marker	Color																																
Action_Transaction	Diamond	Purple																																
Create_Outbound_Delivery	Diamond	Red																																
Create_Sales_Initial_2	Diamond	Blue																																
Create_Standard_ItemData	Diamond	Orange																																
Create_Standard_Overview_2	Diamond	Yellow																																
close windows	Diamond	Green																																
Create_Sales_Initial	Diamond	Orange																																
Create_Sales_Overview	Diamond	Yellow																																
Create_Standard_Overview	Diamond	Orange																																
Create_Standard_Schedule_Line_Data	Diamond	Yellow																																
<b>Layer Level</b>	<p> <b>Siebel Layer Breakdown</b> button shows the breakdown of the selected transaction.</p> <p> <b>Undo Siebel Layer Breakdown</b> returns the graph to the transaction level.</p> <p>In the following figure, the Action_Transaction transaction has been broken down to its layers (Siebel Database, Application, and Web).</p>  <p>This stacked area graph shows Average Response Time (seconds) on the Y-axis (0 to 1) against Elapsed scenario time mm:ss on the X-axis (00:00 to 06:00). The total response time is composed of three layers: Action_Transaction:Database (purple, bottom), Action_Transaction:SiebelServer (green, middle), and Action_Transaction:WebServer (pink, top). All three layers show a similar pattern of peaks and troughs between 0.5s and 1.0s.</p> <table border="1"> <thead> <tr> <th>Layer</th> <th>Color</th> </tr> </thead> <tbody> <tr><td>Action_Transaction:Database</td><td>Purple</td></tr> <tr><td>Action_Transaction:SiebelServer</td><td>Green</td></tr> <tr><td>Action_Transaction:WebServer</td><td>Pink</td></tr> </tbody> </table>	Layer	Color	Action_Transaction:Database	Purple	Action_Transaction:SiebelServer	Green	Action_Transaction:WebServer	Pink																									
Layer	Color																																	
Action_Transaction:Database	Purple																																	
Action_Transaction:SiebelServer	Green																																	
Action_Transaction:WebServer	Pink																																	

<b>Area Level</b>	<p> <b>Siebel Area Breakdown</b> button breaks the data down to its Siebel areas.</p> <p> <b>Undo Siebel Area Breakdown</b> button returns the graph to the layer level.</p> <p>In the following figure, the Web layer of the Action_Transaction transaction has been broken down to its Siebel areas.</p> <div data-bbox="453 460 1204 935"><p style="text-align: center;"><b>Siebel Transaction Average Response Time</b></p><p>Average Response Time (seconds)</p><p>Elapsed scenario time mm:ss</p><p>Action_Transaction:WebServer:SarmIO   Action_Transaction:WebServer:SWSE</p></div>
<b>Script Level</b>	<p> <b>Siebel Script Breakdown</b> button breaks the data down to its Siebel scripts. You can only break down to the script level from the scripting engine area.</p> <p> <b>Undo Siebel Script Breakdown</b> button returns the graph to the sub-area level.</p> <p>You can break a transaction down further to its Siebel script level. You can only break down to the script level from the scripting engine area.</p>

<b>Sub-Area Level</b>	<p> <b>Siebel Sub-Area Breakdown</b> button breaks the data down to its Siebel sub-areas. You can only break down to the sub-area level from the area level.</p> <p> <b>Undo Siebel Sub-Area Breakdown</b> button returns the graph to the area level.</p> <p>In the following figure, the area level of the Action_Transaction transaction has been broken down to its Siebel sub-area.</p> 
<b>Server Level</b>	<p> <b>Siebel Server Breakdown</b> button to group the data by Siebel server.</p> <p> <b>Undo Siebel Server Breakdown</b> button ungroups data in the graph.</p> <p>In the following figure, the Action_Transaction;WebServer:SWSE:Receive Request transaction has been broken down to its Siebel servers. Server level breakdown is usual for pin pointing overloaded servers and for load balancing.</p> 
<b>See also</b>	<p><a href="#">"Siebel Diagnostics Graphs Overview" on page 1661</a></p>

## Siebel Diagnostics Graphs Summary Report

The Siebel Usage section of the Summary Report provides a usage chart for the Siebel layer breakdown. This report is available from the Session Explorer or as a tab in the Analysis window.

<b>Breakdown options</b>	The Siebel Layer Usage section breaks the individual transactions into: <ul style="list-style-type: none"><li>• Web Server</li><li>• Siebel Server</li><li>• Database Layers</li><li>• Total usage time for each transaction</li></ul>
<b>Tips</b>	To view server side diagnostics data from the Summary Report, click the Siebel layer on which you want to perform transaction breakdown. The Siebel Transaction Response Time graph opens displaying the breakdown of the selected transaction.
<b>Note</b>	If you do not see diagnostics data on the Summary Report, check if you are using a user-defined template. To view relevant data, choose a different template from the list of templates, or create and apply a new template. For more information about using templates, see " <a href="#">"Apply/Edit Template Dialog Box" on page 1389</a> ".
<b>See also</b>	<a href="#">"Siebel Diagnostics Graphs Overview" on page 1661</a>


## Siebel Request Average Response Time Graph

This graph displays the response time per HTTP request.

<b>Purpose</b>	The time is computed as the total request response time divided by the total number of instances of the specific request. For example, if a request was executed twice by one instance of transaction A, and once by a second instance of transaction A, and it took three seconds to execute each request, then the average response time is 9/3, or 3 seconds. The request time does not include the nested calls from within each request.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) per area.
<b>Breakdown options</b>	For breakdown options, see " <a href="#">"Siebel Breakdown Levels" on page 1669</a> ".

<b>Tips</b>	You can filter the Siebel graphs by the following fields: <ul style="list-style-type: none"><li>• <b>Transaction Name.</b> Shows data for the specified transaction.</li><li>• <b>Scenario Elapsed Time.</b> Shows data for transactions that ended during the specified time.</li></ul> For more information on filtering, see " <a href="#">Filtering and Sorting Graph Data</a> " on page <a href="#">1394</a> .
<b>See also</b>	<a href="#">"Siebel Diagnostics Graphs Overview"</a> on page <a href="#">1661</a>

### Example




## Siebel Transaction Average Response Time Graph

This graph displays the server response time for the selected area (layer, area, or sub-area) within each transaction, computed as the total response time for that layer or area divided by the total number of relevant transactions.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) per area.
<b>Breakdown options</b>	For breakdown options, see " <a href="#">Siebel Breakdown Levels</a> " on page <a href="#">1669</a> .

<b>Tips</b>	You can filter the Siebel graphs by the following fields: <ul style="list-style-type: none"><li>• <b>Transaction Name.</b> Shows data for the specified transaction.</li><li>• <b>Scenario Elapsed Time.</b> Shows data for transactions that ended during the specified time.</li></ul> For more information on filtering, see " <a href="#">Filtering and Sorting Graph Data</a> " on page 1394.
<b>See also</b>	<a href="#">"Siebel Breakdown Levels" on page 1669</a>

### Example



## Working with Diagnostics


### Siebel DB Diagnostics Graphs

#### ***Siebel DB Diagnostics Graphs Overview***

Siebel DB Diagnostics graphs provide you with performance information for SQLs generated by transactions on the Siebel system. You can view the SQLs for each transaction, identify the problematic SQL queries of each script, and identify at what point problems occurred.

To analyze where problems are occurring, you correlate the data in the Siebel DB Diagnostics graphs with data in the Transaction Response Time graphs.

You begin analyzing these graphs with the transaction graphs that display the average transaction response time during each second of the load test scenario run. For example, the following Average Transaction Response Time graph demonstrates that the average transaction response time for the **query\_for\_contact** transaction was high.



Using the Siebel DB Diagnostics graphs, you can pinpoint the cause of the delay in response time for this transaction.

**Note:** A measurement that is broken down in the Average Transaction Response Time graph will be different from the same measurement broken down in the Siebel DB Side Transactions graph. This is because the Average Transaction Response Time graph displays the average transaction time, whereas the Siebel DB Side Transactions graph displays the average time per transaction event (sum of SQL component response times).

## How to Enable Siebel DB Diagnostics

To generate Siebel DB diagnostics data, you must first install the ERP/CRM Mediator. For information on installing the Mediator, refer to the *HP LoadRunner Installation Guide*.

The Mediator is used to gather and correlate offline diagnostics data from the Siebel server. The Mediator processes the diagnostics data, and then passes it to the Controller.

**Note:** The Mediator must reside in the same LAN as the Siebel server.

To obtain diagnostics data for these graphs, you need to set up the Siebel DB Diagnostics module before running the scenario, and specify the sampling percentage of diagnostics data to include in the diagnostics graphs. For more information on configuring Siebel DB Diagnostics, refer to the *HP LoadRunner Controller User Guide*.

**Note:**

- You should not use the Data Time Range feature (**Tools > Options > Result Collection > Data Time Range**) when analyzing Siebel DB Diagnostics graphs since the data may be incomplete.
- The settings that you configure are per scenario. All scripts in the scenario will run under the same diagnostics configuration.
- To ensure that valid diagnostics data is generated, manually define the transactions in the Vuser script rather than using automatic transactions. Make sure to disable the following options in the run-time settings **General : Miscellaneous** node: **Define each action as a transaction** and **Define each step as a transaction**.

## How to Synchronize Siebel Clock Settings


This task describes how to synchronize the Load Generator and Siebel application server clocks to ensure that the correlation of SQLs to transactions is correct.

1. Choose **Tools > Siebel Database Diagnostics Options**.
2. Select **Apply Application Server time settings**.
3. Click **Add** and enter the information as described in "[Siebel Database Diagnostics Options Dialog Box](#)" on page 1682.
4. Click **OK** to save the data and close the dialog box.

**Note:** You must reopen the results file for time synchronization to take effect.

## Measurement Description Dialog Box

You can view the full SQL statement for a selected SQL element by choosing **Show measurement description** from the Legend window. The Measurement Description dialog box opens displaying the name of the selected measurement and the full SQL statement.



To access	Legend window >
See also	<a href="#">"Siebel Database Breakdown Levels" below</a>

User interface elements are described below:


UI Element	Description
	Break the data down to a lower level.
	Return to the previous level.
	To keep the focus on the Measurement Description dialog box, click the <b>Stay on Top</b> button. This enables you to view the full SQL statement of any measurement by selecting it in the Legend window. Click the button again to remove the focus.
	Click the <b>Breaking Measurement</b> button to display the Transaction Name and SQL Alias Name of the selected measurement.

## Siebel Database Breakdown Levels

You can break down Siebel layers into areas, sub-areas, servers, and scripts to enable you to pinpoint the exact location where time is consumed.

<b>To access</b>	<p>Use one of the following to access breakdown options:</p> <ul style="list-style-type: none"> <li>• &lt;<b>Siebel DB Diagnostics Graphs</b>&gt; &gt; View &gt; <b>Siebel DB Diagnostics</b></li> <li>• &lt;<b>Siebel DB Diagnostics Graphs</b>&gt; &gt; select transaction &gt; short-cut menu &gt; <b>Siebel DB Diagnostics</b></li> <li>• See toolbar options for each breakdown level</li> </ul>
<b>Important information</b>	The breakdown menu options and buttons are not displayed until a transaction is selected.
<b>See also</b>	<a href="#">"Siebel DB Diagnostics Graphs Overview" on page 1675</a>

Siebel Breakdown Levels are described below:


<b>Transaction Level</b>	<p>The following figure displays the top level Average Transaction Response Time graph. The graph displays several transactions. You can break this graph down to show the SQL statements and the SQL stages level.</p>  <p>The graph shows Average Response Time (seconds) on the Y-axis (0 to 130) versus Elapsed scenario time mm:ss on the X-axis (00:00 to 07:30). There are approximately 15 data series, each representing a different transaction or action. Most series remain relatively flat, staying between 0 and 20 seconds. A few series show significant spikes: one series (purple diamonds) rises sharply from ~95s to ~130s around 06:30; another series (orange diamonds) rises from ~40s to ~45s around 05:30; and a third series (black circles) rises from ~20s to ~25s around 06:30. The legend lists the following transactions:</p> <table border="1"> <tr> <td>Action_Transaction</td> <td>close_windows</td> </tr> <tr> <td>Create_Outbound_Delivery</td> <td>Create_Sales_Initial</td> </tr> <tr> <td>Create_Sales_Initial_2</td> <td>Create_Sales_Overview</td> </tr> <tr> <td>Create_Standard_ItemData</td> <td>Create_Standard_Overview</td> </tr> <tr> <td>Create_Standard_Overview_2</td> <td>Create_Standard_Schedule_Line_Data</td> </tr> </table>	Action_Transaction	close_windows	Create_Outbound_Delivery	Create_Sales_Initial	Create_Sales_Initial_2	Create_Sales_Overview	Create_Standard_ItemData	Create_Standard_Overview	Create_Standard_Overview_2	Create_Standard_Schedule_Line_Data
Action_Transaction	close_windows										
Create_Outbound_Delivery	Create_Sales_Initial										
Create_Sales_Initial_2	Create_Sales_Overview										
Create_Standard_ItemData	Create_Standard_Overview										
Create_Standard_Overview_2	Create_Standard_Schedule_Line_Data										

### SQL Statements Level



**Siebel SQL Statements Breakdown** button shows the breakdown of the selected transaction.

In the following figure, the Siebel DB Side Transactions graph displays the Action\_Transaction broken down to its SQL statements.




### SQL Stages Level

 **Measurement Breakdown** button breaks the data down to a lower level.


 **Undo Breakdown Measurement** button returns to the previous level.

In the following figure, the Siebel DB Side Transactions by SQL Stage graph displays Action\_Transaction:SQL-33 broken down to its SQL stage: Prepare, Execute, and Initial Fetch.



### Show measurement description

You can view the full SQL statement for a selected SQL element by choosing **Show measurement description** from the Legend window. The Measurement Description dialog box opens displaying the name of the selected measurement and the full SQL statement.




### See also

["Siebel DB Diagnostics Graphs Overview" on page 1675](#)

## Siebel Database Diagnostics Options Dialog Box

This dialog box enables you to synchronize the Load Generator and Siebel application server clocks.



<b>To access</b>	Tools > Siebel Database Diagnostics Options
<b>Note</b>	You must reopen the results file for time synchronization to take effect.
<b>See also</b>	<a href="#">"How to Synchronize Siebel Clock Settings" on page 1677</a>

User interface elements are described below:


UI Element	Description
<b>Apply Application Server time settings</b>	Enables the synchronized time settings option.
<b>Application Server Name</b>	Enter the name of the Siebel application server.
<b>Time Zone</b>	Enter the time zone of the Siebel application server (GMT or Local). GMT means the application server time is reported in GMT time, and local means the application server time is reported in local time.
<b>Time Difference (sec.)</b>	Enter the time difference (in seconds) between the load generator and the Siebel application server. Use the minus sign ("−") if the time on Siebel application server is ahead of the load generator. For example, if the application server time is two minutes ahead of the load generator time, enter -120 in the time difference field.
<b>Add</b>	Enables you to add an application server's time settings to the list.

UI Element	Description
Delete	Deletes the server breakdown time settings from the list.

## Siebel DB Side Transactions Graph

This graph displays the average transaction execution time in the Siebel database.

X-axis	Elapsed time since the start of the run.
Y-axis	Average response time (in seconds) of each transaction.
Breakdown options	You can break down a transaction in the Siebel DB Side Transactions graph to view its SQL statements. In the following figure, the <b>Action_Transaction</b> transaction is broken down to its SQL statements.
See also	<a href="#">"Siebel DB Diagnostics Graphs Overview" on page 1675</a>



## Siebel DB Side Transactions by SQL Stage Graph

This graph displays the time taken by each SQL, grouped by SQL stage: Prepare, Execute, and Initial Fetch.

X-axis	Elapsed time since the start of the run.
Y-axis	Average time (in seconds) taken to perform each SQL stage.
Breakdown options	<a href="#">"Siebel Database Breakdown Levels" on page 1678</a>

**See also**

["Siebel DB Diagnostics Graphs Overview" on page 1675](#)

## **Siebel SQL Average Execution Time Graph**

This graph displays the average execution time of each SQL performed in the Siebel database.

<b>Purpose</b>	This enables you to identify problematic SQLs regardless of the transaction that produced them. You can then choose <b>Show measurement description</b> from the Legend window to view the full SQL statement. The SQL statements are listed by a numeric ID.
<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) of each SQL.
<b>Breakdown options</b>	<a href="#">"Siebel Database Breakdown Levels" on page 1678</a>
<b>See also</b>	<a href="#">"Siebel DB Diagnostics Graphs Overview" on page 1675</a>


## **Oracle 11i Diagnostics Graphs**

### ***Oracle 11i Diagnostics Graphs Overview***

Oracle 11i Diagnostics graphs provide you with performance information for SQLs generated by transactions on the Oracle NCA system. You can view the SQLs for each transaction, identify the problematic SQL queries of each script, and identify at what point problems occurred.

To analyze where problems are occurring, you correlate the data in the Oracle 11i Diagnostics graphs with data in the Transaction Response Time graphs.

You begin analyzing these graphs with the transaction graphs that display the average transaction response time during each second of the load test scenario run. For example, the following Average Transaction Response Time graph demonstrates that the average transaction response time for the **enter** transaction was high.



Using the Oracle 11i Diagnostics graphs, you can pinpoint the cause of the delay in response time for this transaction.

**Note:**

- A measurement that is broken down in the Average Transaction Response Time graph will be different from the same measurement broken down in the Oracle 11i(DB) Side Transactions graph. This is because the Average Transaction Response Time graph displays the average transaction time, whereas the Oracle 11iDB Side Transactions graph displays the average time per transaction event (sum of SQL component response times).
- vuser\_init** and **vuser\_end** actions in Oracle cannot be broken down. For more information, refer to the *HP Virtual User Generator User Guide*.

## How to Enable Oracle 11i Diagnostics

To generate Oracle 11i Diagnostics data, you must first install the ERP/CRM Mediator. For information on installing the Mediator, refer to the *HP LoadRunner Installation Guide*.

The Mediator is used to gather and correlate offline diagnostics data from the Oracle server. The Mediator processes the diagnostics data, and then passes it to the Controller.

**Note:** The Mediator must reside in the same LAN as the Oracle server.


To obtain diagnostics data for these graphs, you need to set up the Oracle 11i Diagnostics module before running the scenario, and specify the sampling percentage of diagnostics data to include in the diagnostics graphs. For more information on configuring Oracle 11i Diagnostics, refer to the *HP LoadRunner Controller User Guide*.

**Note:**

- The settings that you configure are per scenario. All scripts in the scenario will run under the same diagnostics configuration.
- To ensure that valid diagnostics data is generated, manually define the transactions in the Vuser script rather than using automatic transactions. Make sure to disable the following options in the run-time settings **General : Miscellaneous** node: **Define each action as a transaction** and **Define each step as a transaction**.
- If the Oracle 11i trace cannot be enabled automatically using the built-in mechanism, you can enable it manually in the Vuser script using the **nca\_set\_custom\_dbtrace** and **nca\_set\_dbtrace\_file\_index** functions. This may occur if you are using a custom application that does not have a standard UI.
- You should not use the Data Time Range feature (**Tools > Options > Result Collection > Data Time Range**) when analyzing Oracle 11i Diagnostics graphs since the data may be incomplete.

## **Measurement Description Dialog Box**

This dialog box enables you to view the full SQL statement for a selected SQL element.



<b>To access</b>	Legend window >
<b>See also</b>	<ul style="list-style-type: none"><li>• "<a href="#">Oracle 11i Diagnostics Graphs Overview</a>" on page 1684</li><li>• "<a href="#">Oracle Breakdown Levels</a>" on the next page</li></ul>

User interface elements are described below:

UI Element	Description
	To keep the focus on the Measurement Description dialog box, click the Stay on Top button. This enables you to view the full SQL statement of any measurement by selecting it in the Legend window. Click the button again to remove the focus.
	Click the Breaking Measurement button to display the Transaction Name and SQL Alias Name of the selected measurement.


## Oracle Breakdown Levels

After you have enabled Oracle 11i Diagnostics on the Controller machine and run the load test scenario, you can view the diagnostics data.

<b>To access</b>	Use one of the following to access breakdown options: <ul style="list-style-type: none"><li>• &lt;Oracle Diagnostics Graphs&gt; &gt; View &gt; Oracle Diagnostics</li><li>• &lt;Oracle Diagnostics Graphs&gt; &gt; select transaction &gt; short-cut menu &gt; Oracle Diagnostics</li><li>• See toolbar options for each breakdown level</li></ul>
<b>Important Information</b>	The breakdown menu options and buttons are not displayed until a transaction is selected.
<b>See also</b>	<a href="#">"Oracle 11i Diagnostics Graphs Overview" on page 1684</a>


Oracle Breakdown Levels are described below:

**Transaction Level** The following figure illustrates the top level Average Transaction Response Time graph. The graph displays several transactions.




**SQL Statements Level** The Oracle SQL Statement Breakdown button shows the breakdown of the selected transaction.

In the following figure, the Oracle 11iDB Side Transactions graph displays the Action\_Transaction transaction broken down to its SQL statements.



**SQL Stages Level**

In the following figure, the Oracle 11iDB Side Transactions by SQL Stage graph displays Action\_Transaction:SQL-37 broken down to its SQL stages: Parse Time, Execute Time, Fetch Time, and Other Time. Other Time includes other database time such as bind time.



You can break the data down to a lower level.




Enables you to return to a previous level.

## Oracle 11iDB Side Transactions Graph

This graph displays the average transaction execution time in the Oracle database.

<b>X-axis</b>	Elapsed time of the scenario run.
<b>Y-axis</b>	Response time (in seconds) of each transaction.

<b>Breakdown options</b>	You can break down a transaction in the Oracle 11iDB Side Transactions graph to view its SQL statements. In the following figure, the Action_Transaction transaction is broken down to its SQL statements.
	 <p>To break the displayed elements down further, see "<a href="#">Oracle Breakdown Levels</a>" on page 1687.</p>

## Oracle 11iDB Side Transactions by SQL Stage Graph

This graph displays the time taken by each SQL, divided by the SQL stages: Parse Time, Execute Time, Fetch Time, and Other Time. Other Time includes other database time such as bind time.

<b>X-axis</b>	Elapsed time since the scenario run.
<b>Y-axis</b>	Average response time (in seconds) of each SQL stage.
<b>Breakdown options</b>	<a href="#">"Oracle Breakdown Levels"</a> on page 1687
<b>See also</b>	<a href="#">"Oracle 11i Diagnostics Graphs Overview"</a> on page 1684

## Oracle 11i SQL Average Execution Time Graph

This graph displays the average execution time of each SQL performed in the Oracle database.

<b>Purpose</b>	The graph enables you to identify problematic SQLs regardless of the transaction that produced them.
----------------	------------------------------------------------------------------------------------------------------

<b>X-axis</b>	Elapsed time since the scenario run.
<b>Y-axis</b>	Average response time (in seconds) of each SQL.
<b>Breakdown options</b>	<a href="#">"Oracle Breakdown Levels" on page 1687</a>
<b>Tips</b>	You can select <b>Show measurement description</b> from the Legend window to view the full SQL statement.
<b>Note</b>	The SQL statements are shortened to a numeric indicator.
<b>See also</b>	<a href="#">"Oracle 11i Diagnostics Graphs Overview" on page 1684</a>

## SAP Diagnostics Graphs

### **SAP Diagnostics Graphs Overview**

SAP Diagnostics enables you to pinpoint the root cause of a certain problem (for example, DBA, Network, WAS, Application, OS/HW) quickly and easily, and engage with the relevant expert only, without having to present the problem to a whole team of people.

Using SAP Diagnostics, you can create graphs and reports, which you can present to the relevant expert when discussing the problems that occurred.

SAP Diagnostics also allow an SAP performance expert (in one of the areas of expertise) to perform the required root-cause analysis more quickly and easily.

### **How to Enable SAP Diagnostics**

To generate SAP diagnostics data, you must first install the ERP/CRM Mediator. For information on installing the Mediator, refer to the *HP LoadRunner Installation Guide*.

The Mediator component is used to gather and correlate offline diagnostics data from the SAP server. The Mediator processes the diagnostics data, and then passes it to the Controller.

To obtain diagnostics data for these graphs, you need to set up the SAP Diagnostics module before running the load test scenario, and specify the sampling percentage of diagnostics data to include in the diagnostics graphs. For more information on configuring SAP Diagnostics, refer to the *HP LoadRunner Controller User's Guide*.

#### Important Notes

- In order for SAP Diagnostics to perform effectively, it relies on sound and consistent performance of the SAP software. Malformation or inappropriate configuration of the SAP software could cause inaccuracies in SAP Diagnostics data collection.
- To ensure that valid diagnostics data is generated, manually define the transactions in the Vuser

script rather than using automatic transactions. Make sure to disable the following options in the run-time settings **General: Miscellaneous** node: **Define each action as a transaction** and **Define each step as a transaction**.

- The ERP/CRM Mediator requires an installation of SAPGUI 6.20 or 6.40.
- If no connection can be established between the ERP/CRM Mediator and one of the SAP application servers, no work process or OS monitor data is collected for that server. However, as long as there is a connection to one of the servers, statistical records for response time breakdown are still available.
- The settings that you configure are per scenario. All scripts in the scenario will run under the same diagnostics configuration.

## How to Configure SAP Alerts

SAP Diagnostics comes with a set of alert rules with pre-defined threshold values.

When you open a LoadRunner results file (.lrr) in Analysis, these alert rules are applied to the load test scenario results, and if a threshold value is exceeded, Analysis generates an alert that there is a problem.

Before opening a LoadRunner results file, you can define new threshold values for the alert rules using the Alerts Configuration dialog box. Then, when you open the results file, the customized alert rules are applied.

**Note:** When an Analysis session is open, the Alerts Configuration dialog box is not editable. To edit thresholds in the Alerts Configuration dialog box, close all open sessions.

This task describes how to define threshold values for alert rules when analyzing load test scenario results.


1. Close all open Analysis sessions.
2. From the **Tools** menu, select **SAP Diagnostics Alerts Configuration**.
3. The **Generate alert if** column lists the rules. Set the threshold for each rule in the **Threshold** column.
4. By default, all pre-defined alert rules are enabled. To disable an alert rule, clear the check box next to that rule.
5. Click **OK** to apply your changes and close the Alerts Configuration dialog box.

**Note:** Modifying the alert rules does not affect the results of a saved Analysis session. You need to re-analyze the results in order for new settings to take effect.

## SAP Diagnostics - Guided Flow Tab

You open the SAP Diagnostics graphs from the Analysis Summary Report or from **Session Explorer > Graphs > SAP Diagnostics - Guided Flow**.

This tab remains open throughout the Analysis application flow, and its content varies according to the breakdown flow.




User interface elements are described below:

UI Element	Description
Primary Graph Pane	<p>The upper pane of the SAP Diagnostics - Guided Flow tab is referred to as the <i>primary graph pane</i>. This pane displays graphs of the transactions and their broken down dialog steps or components, and other associated resources.</p> <p>You break down the graphs displayed in this pane using the breakdown options provided in the right pane of the guided flow (see "<a href="#">SAP Breakdown Task Pane</a>" on page 1700).</p> <p>You can open the displayed graph in full view by clicking the <b>Enlarge Graph</b> button in the top right corner of this pane. An enlarged version of the graph opens in a new tab.</p>

UI Element	Description
<b>Secondary Graph Pane</b>	<p>The lower pane of the SAP Diagnostics - Guided Flow tab is referred to as the <b>secondary graph pane</b> and displays graphs showing secondary information supporting the graph displayed in the primary graph pane.</p> <p>To see the legend for the graph displayed in this pane, click the <b>Graph Legend</b> button in the top right corner. To see all the data in the Legend, scroll along the horizontal scroll bar.</p> <p>You can open the displayed graph in full view by clicking the <b>Enlarge Graph</b> button in the top right corner of this pane. An enlarged version of the graph opens in a new tab.</p>
<b>Task Pane</b>	<p>The pane on the right side of the SAP Diagnostics - Guided Flow tab is referred to as the <i>task pane</i>. You use the task pane to choose the level of breakdown you want to view, to filter and group transaction and server information, and to navigate backwards and forwards through the broken down graphs.</p> <p>For more information, see "<a href="#">SAP Breakdown Task Pane</a>" on page 1700.</p>

## SAP Diagnostics Application Flow

The following diagram depicts the general flow of SAP Diagnostics:



The main view of SAP Diagnostics displays all of the transactions in a scenario run for which there is SAP diagnostics data. Each transaction can be broken down into server-time components, or

first into the dialog steps that comprise a transaction, and then into server-time components. The server components can further be broken down into sub-components or other related data.


There are three independent/parallel views: **Dialog Steps per Second**, **OS Monitor**, and **Work Processes**. These do not generally participate in the breakdown flow, and you may choose to display or hide them.

## Dialog Steps per Second Graph

This graph represents the number of dialog steps that ran on all the servers during each second of the load test scenario run.

<b>X-axis</b>	Elapsed scenario time (in hh:mm:ss).
<b>Y-axis</b>	Number of dialog steps per second.
<b>See also</b>	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"Vuser Graphs" on page 1475</a> <a href="#">"Work Processes Graph" on page 1707</a> <a href="#">"OS Monitor Graph" below</a>

### Example




## OS Monitor Graph

This graph represents the operating system resources that were measured throughout the load test scenario run.


<b>X-axis</b>	Elapsed scenario time (in hh:mm:ss).
<b>Y-axis</b>	Resource value.
<b>Note</b>	This graph is available only when a single server filter is applied.
<b>See also</b>	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"Dialog Steps per Second Graph" above</a> <a href="#">"Work Processes Graph" on page 1707</a>

### Example



## SAP Alerts Configuration Dialog box

This dialog box enables you to define threshold values for alert rules used when opening the results file (.lrr) in Analysis.



<b>Important information</b>	Modifying the alert rules does not affect the results of a saved Analysis session. You need to re-analyze the results in order for new settings to take effect.
<b>See also</b>	<a href="#">"SAP Diagnostics Graphs Overview" on page 1691</a>

User interface elements are described below:

UI Element	Description
<b>Enabled</b>	By default, all pre-defined alert rules are enabled. To disable an alert rule, clear the check box next to that rule.
<b>Generate alert if</b>	The <b>Generate alert if</b> column lists the rules.
<b>Threshold</b>	Set the threshold for each rule in the <b>Threshold</b> column.

## SAP Alerts Window

This Window displays a list of alerts related to the data displayed in the current graph(s) shown in the Analysis window.

<b>To access</b>	<b>Windows &gt; SAP Alerts</b>
<b>See also</b>	<a href="#">"SAP Alerts Configuration Dialog box" on the previous page</a> <a href="#">"How to Configure SAP Alerts" on page 1692</a>

User interface elements are described below:


UI Element	Description
<b>Type</b>	<p>Displays one of the following icons indicating the type of alert:</p> <p> <b>Standard Alert.</b> This alert is generated in the context of a transaction and/or server if the conditions of a pre-defined alert rule are met.</p> <p> <b>Major Alert.</b> There are two types of alerts:</p> <ul style="list-style-type: none"> <li>• <b>General Application Problem Alert.</b> If a standard alert was generated in the context of a transaction, and the same alert was generated in the context of all other transactions running in the same time frame, then a major alert of this type is generated, indicating that there is a general application problem.</li> </ul> <p><b>Note:</b> If a Dialog Step filter is applied (for a single dialog step), then this alert is not generated.</p> <ul style="list-style-type: none"> <li>• <b>Server-Specific Problem Alert.</b> This alert is generated for a specific server if a certain measurement on that server exceeds its threshold, while the overall server performance for that measurement is satisfactory. This type of alert indicates that there is a server related problem.</li> </ul> <p><b>Note:</b> Server-Specific Problem alerts are generated only when the current server context is "All Servers".</p>
<b>Time interval</b>	The time interval during which the problem occurred.
<b>Transaction/Server</b>	The name of the transaction and server where problem occurred.
<b>Description</b>	A description of the alert.
<b>Recommended Step</b>	Recommends what to do in order to understand the problem on a deeper level.
<b>Action</b>	A link to a graph representing the data described in the alert, allowing for a more graphic display of the alert. Double-click the link to open the graph.

## SAP Application Processing Time Breakdown Graph

This graph displays the behavior of resources associated with application processing time, namely ABAP time and CPU time.

<b>X-axis</b>	Elapsed load test scenario time (in hh:mm:ss).
<b>Y-axis</b>	Average time per dialog step (in seconds).
<b>See also</b>	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"SAP Secondary Graphs" on page 1707</a>

### Example



## SAP Primary Graphs

You view the SAP Diagnostics graphs in the primary graph pane.

You can open the graph in full view by clicking  in the top right corner of the primary graph pane. An enlarged version of the graph opens in a new tab.

To filter or group data displayed in these graphs, see ["SAP Breakdown Task Pane" on page 1700](#).


## SAP Average Dialog Step Response Time Breakdown Graph

This graph represents a breakdown of the average dialog step response time of a specific transaction. The graph displays the Network Time, Server Response Time, (including the GUI time), and Other Time (the time taken for the client to process the dialog step) of a single transaction.

<b>X-axis</b>	Elapsed time since the start of the run (in hh:mm:ss).
---------------	--------------------------------------------------------

<b>Y-axis</b>	The average response time divided by the number of dialog steps (in seconds).
<b>Breakdown options</b>	<p><b>Components</b>  This option opens the "SAP Server Time Breakdown Graph" on page 1703</p> <p><b>Dialog Steps</b>  This option opens the "SAP Server Time Breakdown (Dialog Steps) Graphs" on page 1703</p>
<b>See also</b>	<p>"SAP Breakdown Task Pane" on the next page</p> <p>"SAP Secondary Graphs" on page 1707</p> <p>"SAP Breakdown Task Pane" on the next page</p>

### Example



## SAP Average Transaction Response Time Graph

This graph displays all the SAP-related transactions in the load test scenario.

<b>X-axis</b>	Elapsed time since the start of the run.
<b>Y-axis</b>	Average response time (in seconds) of each transaction
<b>Breakdown graph</b>	"SAP Average Dialog Step Response Time Breakdown Graph" on the previous page
<b>Tips</b>	<p>Select a transaction in one of the following ways:</p> <ul style="list-style-type: none"> <li>Select the transaction from the Breakdown transaction: list in the task pane.</li> <li>Highlight the transaction by selecting the line representing it in the graph.</li> <li>Select the transaction from the graph legend. This highlights the line in the graph.</li> </ul>

<b>See also</b>	"SAP Breakdown Task Pane" below "SAP Secondary Graphs" on page 1707 "SAP Breakdown Task Pane" below
-----------------	-----------------------------------------------------------------------------------------------------------

## SAP Breakdown Task Pane

The task pane enables you to choose the level of breakdown you want to view, to filter and group transaction and server information, and to navigate backwards and forwards through the broken down graphs.

<b>To access</b>	Session Explorer > Graphs > SAP Diagnostics > SAP Diagnostics - Guided Flow
<b>See also</b>	"SAP Diagnostics Graphs Overview" on page 1691

### SAP Breakdown Toolbar

User interface elements are described below:

UI Element	Description
	<b>Back.</b> Click to view previous breakdown graph, or to ungroup grouped data.
	<b>Next.</b> Click to view next breakdown graph.
	<b>Home.</b> Click to return to the initial SAP Average Transaction Response Time graph.
	<b>Help.</b> Click to get help on the breakdown options.

### Breakdown Options

To break down SAP diagnostics data, choose the breakdown and filter options from the task pane.

User interface elements are described below:

UI Element	Description
<b>Break down transaction</b>	Select a transaction from this list to display the average dialog step response time breakdown.

UI Element	Description
<b>Break down server time into</b>	Displays the breakdown options for the Average Dialog Step Response Time Breakdown graph. <ul style="list-style-type: none"><li>• Select <b>Components</b> to view a breakdown of the transaction's server components, namely database time, interface time, application processing time, and system time.</li><li>• Select <b>Dialog Steps</b> to view a breakdown of the transaction's dialog steps.</li></ul>
<b>Break down dialog step &lt;dialog step&gt;</b>	Break down a dialog step into its server-time components, namely database time, interface time, application processing time, and system time.
<b>View data associated with &lt;component&gt;</b>	Break down a server-time component (database time; interface time; application processing time; system time) to view data associated with it.
<b>No available breakdown</b>	There are no further breakdown options.
<b>Apply</b>	Click to apply the selected breakdown option.

## Current filter settings

This section displays the filter/grouping settings of the graph currently displayed in the primary graph pane.

User interface elements are described below:

UI Element	Description
<b>From/To</b>	Enter values (in hh:mm:ss) to filter the graph over a specified time interval.
<b>Transaction</b>	Displays the name of the transaction represented in the graph.
<b>Dialog Step</b>	Displays the name of the dialog step represented in the graph.
<b>Server</b>	Displays the name of the server represented in the graph.

## Edit filter settings

Click this button to modify filter or grouping settings. When you click **Edit Filter Settings** the filter/grouping options become editable.

User interface elements are described below:


UI Element	Description
<b>Filter</b>	<p>Use this option to filter the current graph by time interval, transaction, dialog step, and/or server.</p> <ul style="list-style-type: none"> <li>• <b>From/To.</b> Enter values (in hh:mm:ss) to filter the graph over a specified time interval.</li> <li>• <b>By Transaction.</b> Filter the graph to display information about a specific transaction by selecting the transaction from the list.</li> <li>• <b>By Dialog Step.</b> Filter the graph to display information about a specific dialog step by selecting the dialog step from the list.</li> <li>• <b>By Server.</b> Filter the graph to display information about a server by selecting the server name from the list.</li> </ul> <p><b>Note:</b> Only servers associated with the data displayed in the current graph are listed in the By Server list</p>
<b>Group</b>	<p>Use this option to group the data represented in the graph by transaction or by server. Select a transaction, component or subcomponent from the list.</p> <ul style="list-style-type: none"> <li>• <b>By Transaction.</b> Select this check box to group by transaction.</li> <li>• <b>By Server.</b> Select this check box to group by server.</li> </ul> <p><b>Note:</b> After applying grouping to a graph, you need to ungroup the data in order to apply further breakdown options. To ungroup grouped data, click the <b>Back</b> button on the toolbar.</p> <p><b>Important:</b> When you open a saved session, the <b>Back</b> is disabled. If you have grouped data, you need to click the Home button, or open a new SAP Diagnostics - Guided Flow tab to restart SAP breakdown.</p>
<b>OK</b>	<p>Click <b>OK</b> to apply the chosen filter/grouping settings. The <b>Current filter settings</b> area displays the chosen settings in non-editable mode.</p> <p><b>Notes:</b></p> <ul style="list-style-type: none"> <li>• Global filtering is enabled when viewing SAP Diagnostics graphs (special SAP view) but cannot be applied on these graphs.</li> <li>• Local filtering is disabled in the SAP Diagnostics - Guided Flow tab. To apply local filters to a SAP Diagnostics graph displayed in the Guided Flow tab, open the graph in a new tab by clicking the Enlarge Graph button.</li> </ul>

## SAP Server Time Breakdown (Dialog Steps) Graphs

This graph displays the dialog steps of a particular transaction.

<b>X-axis</b>	Elapsed time since the start of the run (in hh:mm:ss).
<b>Y-axis</b>	The average response time per dialog step (in seconds).
<b>Breakdown graph</b>	<a href="#">"SAP Server Time Breakdown Graph" below</a>
<b>See also</b>	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"SAP Secondary Graphs" on page 1707</a> <a href="#">"SAP Breakdown Task Pane" on page 1700</a>

### Example




## SAP Server Time Breakdown Graph

This graph represents the server-time components of a single transaction, namely database time, application processing time, interface time, and system time.

<b>X-axis</b>	Elapsed time since the start of the run (in hh:mm:ss).
<b>Y-axis</b>	Represents the average response time per dialog step (in seconds).
<b>Breakdown graphs</b>	<ul style="list-style-type: none"><li><a href="#">"SAP Database Time Breakdown Graph" on the next page</a></li><li><a href="#">"SAP Application Processing Time Breakdown Graph" on page 1698</a></li><li><a href="#">"SAP System Time Breakdown Graph" on page 1706</a></li><li><a href="#">"SAP Interface Time Breakdown Graph" on page 1706</a></li></ul>
<b>Tips</b>	In the task pane, select a component from the <b>View data associated with</b> box.

<b>See also</b>	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"SAP Secondary Graphs" on page 1707</a> <a href="#">"SAP Breakdown Task Pane" on page 1700</a>
-----------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------

### Example




## SAP Database Time Breakdown Graph

This graph displays the behavior of resources associated with database time, namely time taken to access a record, database time, and the number of records accessed per dialog step.


<b>X-axis</b>	Elapsed time since the start of the run (in hh:mm:ss).
<b>Y-axis</b>	Represents the resource value per dialog step (in msec).
<b>Tips</b>	You can open the graph in full view by clicking  in the top right corner of the primary graph pane. An enlarged version of the graph opens in a new tab.
<b>See also</b>	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"SAP Secondary Graphs" on page 1707</a>

### Example



## SAP Diagnostics Summary Report

This report displays a list of major alerts generated when opening the Analysis session, and a summary of the SAP diagnostics data.



To access	<p>Use one of the following:</p> <ul style="list-style-type: none"><li>• <b>Session Explorer &gt; Reports &gt; Summary Report &gt; Major Alerts</b></li><li>• <b>Session Explorer &gt; Reports &gt; Summary Report &gt; SAP Diagnostics Summary</b></li></ul>
Note	If you do not see diagnostics data on the Summary Report, check if you are using a user-defined template. To view relevant data, choose a different template from the list of templates, or create and apply a new template. For more information about using templates, see " <a href="#">"Apply/Edit Template Dialog Box" on page 1389</a> ".
See also	<a href="#">"SAP Diagnostics Graphs Overview" on page 1691</a>

### SAP Diagnostics Summary

User interface elements are described below:

UI Element	Description
Transaction	Individual transactions. You can click a transaction name to display the server time breakdown for that transaction.
SAP Diagnostics Layers	Relative server-time breakdown in layers. Click a layer to display data associated with the component.
Total time	Total usage time for each transaction.

### Major Alerts

User interface elements are described below:


UI Element	Description
Time Interval	The time during which the problem occurred.
Transaction/Server	Which transaction and server were involved.
Description	A description of the alert.
Action	This column provides a link to a graphic depiction of the problem.

## SAP Interface Time Breakdown Graph

This graph displays the behavior of resources associated with interface time, namely GUI time, RFC time, and roll-wait time.

X-axis	Elapsed load test scenario time (in hh:mm:ss)
Y-axis	Average response time per dialog step (in seconds).
See also	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"SAP Secondary Graphs" on the next page</a>

### Example




## SAP System Time Breakdown Graph

This graph displays the behavior of the sub-components of the system time component, namely the dispatcher wait time, the load and generation time, and the roll-in and roll-out times.

X-axis	Elapsed load test scenario time (in hh:mm:ss)
Y-axis	Average response time per dialog step (in seconds)
See also	<a href="#">"SAP Breakdown Task Pane" on page 1700</a> <a href="#">"Secondary Graph Pane" on page 1694</a>

### Example



## SAP Secondary Graphs

The secondary graph pane of the SAP Diagnostics - Guided Flow tab displays graphs that support the graph displayed in the primary graph pane. You can correlate over time only one graph displayed in the secondary graph pane.

To see the legend for the graph displayed in this pane, click the **Graph Legend** button  in the top right corner. To see all the data in the Legend, scroll along the horizontal scroll bar.

You can open the displayed graph in full view by clicking the **Enlarge Graph** button  in the top right corner of this pane. An enlarged version of the graph opens in a new tab.

You view the following graphs in the secondary graph pane:

- "["Vuser Graphs" on page 1475](#)
- "["Dialog Steps per Second Graph" on page 1695](#)
- "["Work Processes Graph" below](#)
- "["OS Monitor Graph" on page 1695](#)

## Work Processes Graph

This graph represents the number and distribution of work processes that ran throughout the load test scenario.

<b>X-axis</b>	Elapsed scenario time (in hh:mm:ss).
<b>Y-axis</b>	Number of work processes.
<b>Note</b>	This graph is available only when a single server filter is applied.

**See also**


["SAP Breakdown Task Pane" on page 1700](#)

["Vuser Graphs" on page 1475](#)

["Dialog Steps per Second Graph" on page 1695](#)

["OS Monitor Graph" on page 1695](#)

**Example**



## J2EE & .NET Diagnostics Graphs

### *J2EE & .NET Diagnostics Graphs Overview*

The J2EE & .NET Diagnostics graphs in LoadRunner Analysis enable you to trace, time, and troubleshoot individual transactions and server requests through J2EE & .NET Web, application, and database servers. You can also pinpoint problem servlets and JDBC calls to maximize business process performance, scalability, and efficiency.

The J2EE & .NET Diagnostics graphs are comprised of two groups:

- **J2EE & .NET Diagnostics Graphs.** These graphs show you the performance of requests and methods generated by virtual user transactions. They show you the transaction that generated each request.
- **J2EE & .NET Server Diagnostics Graphs.** These graphs show you the performance of all the requests and methods in the application you are monitoring. These include requests generated by virtual user transactions and by real users.

### **How to Enable Diagnostics for J2EE & .NET**

To generate Diagnostics for J2EE & .NET data, you must first install HP Diagnostics.

Before you can use HP Diagnostics with LoadRunner, you need to ensure that you have specified the Diagnostics Server details in LoadRunner. Before you can view Diagnostics for J2EE & .NET data in a particular load test scenario, you need to configure the Diagnostics parameters for that scenario. For more information about Configuring HP Diagnostics to work with LoadRunner, refer to the *HP LoadRunner Controller User Guide*.


**Note:** To ensure that valid J2EE/.NET diagnostics data is generated during the scenario run, you must manually mark the beginning and end of each transaction in the Vuser script, rather than using automatic transactions.

## Viewing J2EE to SAP R3 Remote Calls

The *Remote Function Call* (RFC) protocol in SAP allows communication to take place between SAP J2EE and SAP R3 environments. When remote calls take place between SAP J2EE and SAP R3 environments, Analysis displays information about the RFC functions, including the name of each function.

You view information about RFC functions by breaking down the SAP R3 layer. You can view the RFC function information in a graph display or in the Chain Of Calls window.


1. Go to the **J2EE/.NET Diagnostics Usage** section of the Summary Report. Next to the relevant transaction, click the color representing the **SAP.R3** layer.



The J2EE/.NET - Transaction Time Spent in Element graph opens, representing the SAP.R3 layer.

2. Right click the graph and choose **J2EE/.NET Diagnostics > Break down the class to methods**.
3. Break down the graph further by right clicking the graph and choosing **J2EE/.NET Diagnostics > Break down the method to SQLs**.


The graph is broken down into the different RFC functions.



4. To view the name of each RFC function, right click an RFC measurement in the **Measurement**

column in the graph legend and choose **Show measurement description**.

The Measurement Description dialog box opens. The name of the RFC function is displayed in the **SQL** box.




## View RFC function information in the Chain Of Calls window

1. Go to the **J2EE/.NET Diagnostics Usage** section of the Summary Report. Next to the relevant transaction, click the color representing the **SAP.R3** layer.

The J2EE/.NET - Transaction Time Spent in Element graph opens, representing the SAP.R3 layer.

2. Right click the graph and choose **J2EE/.NET Diagnostics > Show chain of calls**.

The Transaction chain of calls window opens. When you click any of the RFC functions, in the **Measurement** column, the name of the function is displayed in the lower pane in the **RFC Name** tab.



## J2EE & .NET Diagnostics Data

The J2EE & .NET Diagnostics graphs provide an overview of the entire chain of activity on the server side of the system. At the same time, you can break down J2EE/.NET layers into classes and methods to enable you to pinpoint the exact location where time is consumed. In addition, you can view custom classes or packages that you set the J2EE/.NET probe to monitor. You can also view the transaction chain of calls and call stack statistics to track the percentage of time spent on each part of the transaction.


You can correlate the end user response time with the Web server activity (Servlets and JSPs data), application server activity (JNDIs), and back-end activity of database requests (JDBC methods and SQL queries).

## Example Transaction Breakdown

The following graphs illustrate the breakdown of a transaction to its layers, classes, and methods.


### Transaction Level

The following figure shows the top level Average Transaction Response Time graph. The graph displays several transactions: **Birds**, **Bulldog**, **Checkout**, **Start**, and so on.




### Layer Level

In the following figure, the **Start** transaction has been broken down to its layers (DB, EJB, JNDI, and Web). In J2EE/.NET transactions, the Web layer is generally the largest.




## Class Level

In the following figure, the Web layer of the **Start** transaction has been broken down to its classes.



### Method/Query Level

In the following figure, the **weblogic.servlet.FileServlet** component of the **Web** layer of the **Start** transaction has been broken down to its methods.



**Note:** Some JDBC methods can invoke SQLs which can be broken down further. In this case there is another level of breakdown, that is SQL Statements. For the methods that can not be further broken down into SQL statements when reaching this level of breakdown, you see [NoSql](#).

## Cross VM Analysis

When a server request makes a remote method invocation, the J2EE & .NET Diagnostics graphs display certain measurements relating to the classes and methods involved in these requests. These measurements are displayed at a layer, class and method level. The VM making the call is referred to as the *caller VM*, and the VM that executes the remote call is the *callee VM*.

The measurements are described below:

Measurements	Description
Cross VM Layer	A measurement that represents a dummy layer that integrates the data from the remote classes and methods in server requests that take place across two or more virtual machines.
Remote-Class	A measurement that represents a dummy class that integrates the data from the remote methods in server requests that take place across two or more virtual machines.
Remote-Class: Remote Method	A measurement that represents a dummy method. Remote-Class: Remote Method measures the total time, call count, exclusive latency, minimum and maximum values, standard deviation, and so on of the methods that are executed remotely, relative to the caller virtual machine.


**Note:** Since this data is measured on the caller virtual machine the exclusive latency will include all of the time required for making the remote method invocation such as network latency.

## Using the J2EE & .NET Breakdown Options

J2EE & .NET breakdown options are described.

To access	<p>Use one of the following to access breakdown options:</p> <ul style="list-style-type: none"><li>• &lt;J2EE &amp; .NET Graphs&gt; &gt; View &gt; J2EE &amp; .NET Diagnostics</li><li>• &lt;J2EE &amp; .NET Diagnostics Graphs&gt; &gt; select transaction &gt; short-cut menu &gt; J2EE &amp; .NET Diagnostics</li><li>• See toolbar options for each breakdown level</li></ul>
Notes	<ul style="list-style-type: none"><li>• The breakdown menu options and buttons are not displayed until an element (transaction, server request, layer) is selected.</li><li>• If there is no URI in the SQL, URI-None appears in front of the full measurement description in the Measurement Description dialog box.</li></ul>
See also	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

User interface elements are described below :

UI Element	Description
<b>&lt;Right-click&gt; transaction in Average Response Time Graph</b>	<p>Choose J2EE/.NET Diagnostics &gt; Show Server Requests. A new graph opens showing the breakdown of the selected transaction. The name of the transaction is displayed in the Breaking Measurement box.</p> <p>Breaking Measurement: patient_login:EJB.SessionBean </p>  <p>You can view the full SQL statement for a selected SQL element by choosing <b>Show measurement description</b> from the Legend window right-click menu. The Measurement Description dialog box opens displaying the name of the selected measurement and the full SQL statement.</p>
	<p>To view transaction properties for the breakdown measurement, click the <b>Breaking Measurement</b> button. To disable this feature, choose <b>View &gt; Display Options</b>, and clear the <b>Show Breaking Measurement</b> check box.</p>
	<p>Select <b>View &gt; J2EE/.NET Diagnostics &gt; Break down the server request to layers</b>, or click the measurement breakdown button in the toolbar above the graph.</p> <p><b>Note:</b> The option in the J2EE/.NET Diagnostics menu, and the tool tip of the measurement breakdown button, vary according to the element that you want to break down. For example, when you select a server request, the menu option and tool tip are <b>Break down server request to layers</b>.</p>

UI Element	Description
	Select <b>View &gt; J2EE/.NET Diagnostics &gt; Show VM</b> , or click the <b>Show VM</b> button in the toolbar above the graph. This breaks the data down to the application host name (VM).
	Select <b>View &gt; J2EE/.NET Diagnostics &gt; Undo Break down the server request to layers</b> , or click the <b>Undo &lt;Measurement Breakdown&gt;</b> button in the toolbar above the graph.  <b>Note:</b> The option in the J2EE/.NET Diagnostics menu, and the tool tip of the measurement breakdown button, vary according to the element whose breakdown you want to undo. For example, when you select a layer, the menu option and tool tip are Undo break down server request to layers.
	Select <b>View &gt; J2EE/.NET Diagnostics &gt; Hide VM</b> , or click the <b>Hide VM</b> button in the toolbar above the graph.
	Display the chain of call or call stack statistics in the measurements tree window: Drag the orange time line on to the graph to the time specifying the end of the period for which you want to view data, and select <b>View &gt; J2EE/.NET Diagnostics &gt; Show Chain of Calls</b> , or click the <b>Show Chain of Calls</b> button in the toolbar above the graph.  <b>Note:</b> A measurement that is broken down in the Average Method Response Time in Transactions graph will be different from the same measurement broken down in the J2EE/.NET - Transaction Time Spent in Element graph. This is because the J2EE/.NET - Average Method Response Time in Transactions graph displays the average transaction time, whereas the J2EE/.NET - Transaction Time Spent in Element graph displays the average time per transaction event (sum of method execution time).

## **Viewing Chain of Calls and Call Stack Statistics**

You can view the chain of calls for transactions and methods. The chain of calls answers the question "Whom did I call?"

You can also view the call stack statistics for methods. Call stack statistics answer the question "Who called me?"

Chain of call and call stack statistics data are shown in the measurements tree window. The title of the window changes depending on which kind of data you are viewing.


- To set the point to which the measurements tree window relates, you must drag the orange time line to the desired spot.
- To view transaction call chains, right-click a component and choose **J2EE/.NET Diagnostics > Show Chain of Calls**. The Chain of Calls window opens

displaying the chain of calls from the parent transaction downwards.

- To view method statistics, in the Chain of Calls window right-click a method and choose **Show Method Chain of Calls** or **Show Method Call Stack Statistics**.


## The Chain of Calls Windows

You use the Chain of Calls window to view the components that the selected transaction or method called. In the following figure, all the calls in the critical path of the Start server-side transaction are displayed.



**Note:** Each red node signifies the most time consuming child of its parent.

You use the Call Stack Statistics window to view which components called the selected component. In the following figure, the **FileServlet.service** was called by Start (Server), which was called by Start (Client), and so on, down to the transaction at the bottom of the chain.



## ***Understanding the Chain of Calls Window***

User interface elements are described below:

UI Element	Description
	<b>Switch to Method Chain of Calls.</b> When the call stack statistics data is displayed, displays the method chain of calls data (only if the root is a method).
	<b>Switch to Method Call Stack Statistics.</b> When the method chain of calls data is displayed, displays the method call stack statistics data (only if the root is a method).
	<b>Show Method Chain of Calls.</b> Displays the Chain of Calls window.
	<b>Show Method Call Stack Statistics.</b> Displays the Call Stack Statistics window.
	<b>Properties.</b> Hides or displays the properties area (lower pane).
	<b>Columns.</b> Enables you to select the columns shown in the Calls window. To display additional fields, drag them to the desired location in the Calls window. To remove fields, drag them from the Calls window back to the Columns chooser.
	<b>Expand All.</b> Expands the entire tree.
	<b>Collapse All.</b> Collapses the entire tree.
	<b>Expand Worst Path.</b> Expands only the parts of the path on the critical path.

UI Element	Description
<b>Save to XML File</b>	Saves the tree data to an XML file.
<b>Method Properties</b>	Area. Displays the full properties of the selected method.
<b>SQL Query</b>	Displays the SQL query for the selected method. (For Database only.)The following columns are available in the Chain of Calls window:

The following columns are available in the Chain of Calls window:

Column	Description
<b>Measurement</b>	Name of the method, displayed as <b>ComponentName:MethodName</b> . In the case of a database call, query information is also displayed. The percent shown indicates the percentage of calls to this component from its parent.
<b>% of Root Method</b>	Percentage of the total time of the method from the total time of the root tree item.
<b>No of Calls</b>	Displays the amount of times this transaction or method was executed.
<b>Avg Response Time</b>	Response time is the time from the beginning of execution until the end. Average response time is the total response time divided by the number of divided by the number of instances of the method.
<b>STD Response Time</b>	The standard deviation response time.
<b>Min Response Time</b>	The minimum response time.
<b>Max Response Time</b>	The maximum response time.
<b>% of Caller</b>	Displays the percentage of method time in relation the parent method time.
<b>Total time</b>	Displays the total method execution time, including the child execution time.

The following columns are available in the Call Stack Statistics window:

Column	Description
<b>Measurement</b>	Name of the method, displayed as <b>ComponentName.MethodName</b> . In the case of a database call, query information is also displayed. The percent shown indicates the percentage of calls to this component from its child.

Column	Description
<b>% of Root Method</b>	Percentage of the total time of the transaction (or method) from the total time of the root tree item.
<b>No. of Calls to Root</b>	Displays the amount of times this transaction or method was executed.
<b>Avg Time Spent in Root</b>	Time spent in root is the time that the sub-area spent in the root sub-area/area/transaction.  Average Time Spent in Root time is the total time spent in the root divided by the number of instances of the method.
<b>STD Time Spent in Root</b>	The standard deviation time spent in the root.
<b>Min Time Spent in Root</b>	The minimum time spent in the root.
<b>Max Time Spent in Root</b>	The maximum time spent in the root.
<b>% of Called</b>	Displays the percentage of method time in relation the child method time.
<b>Total Time Spent in Root</b>	Displays the total method execution time, including the child execution time.

## Graph Filter Properties

You can filter the J2EE & .NET Diagnostics graphs so that the displayed data is more suitable to your needs. You can filter using the following methods:

- Before opening a graph, enter filter criteria in the **Graph Properties** box of the [Open Graph](#) dialog box. For more information, see "[Open a New Graph Dialog Box](#)" on page 1359.
- From an open graph, enter filter criteria in the **Filter condition** fields in a filter dialog box. For more information, see "[Filter Dialog Boxes](#)" on page 1405 and "[Drilling Down in a Graph](#)" on page 1412.

User interface elements are described below:

UI Element	Description
<b>Class Name</b>	Shows data for specified classes.

UI Element	Description
Layer Name	Shows data for specified layers.
Scenario Elapsed Time	Shows data for transactions that ended during the specified time.
SQL Logical Name	Shows data for specified SQL logical names. Due to the length of some SQL names, after you choose an SQL statement it is assigned a "logical name." This logical name is used in the filter dialog, legend, grouping, and other places in place of the full SQL statement. You can view the full SQL statement in the Measurement Description dialog box ( <b>View &gt; Show Measurement Description</b> ).
Transaction Name - J2EE/.NET	Shows data for a specified transaction.

Some JDBC methods have the ability to invoke SQL's (each method can invoke several different SQL's) so there is another level of breakdown which is the SQL statements.


**Note:** For the methods that do not have SQL statement when reaching this level of breakdown you see **NoSql**.

## ***J2EE/.NET - Average Method Response Time in Transactions Graph***

This graph displays the average response time for the server side methods, computed as Total Method Response Time/Number of Method calls. For example, if a method was executed twice by an instance of transaction A and once by another instance of the same transaction, and it took three seconds for each execution, the average response time is 9/3, or 3 seconds. The method time does not include calls made from the method to other methods.

X-axis	Elapsed time.
Y-axis	Average response time (in seconds) per method
Breakdown options	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>
See also	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### **Example**




## J2EE/.NET - Average Number of Exceptions in Transactions Graph

This graph displays the average number of code exceptions per method, transaction, or request that were monitored during the selected time range.

<b>X-axis</b>	Elapsed time.
<b>Y-axis</b>	Represents the number of events.
<b>Breakdown options</b>	To break the displayed elements down further, see " <a href="#">Using the J2EE &amp; .NET Breakdown Options</a> " on page 1715.
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview"</a> on page 1708

### Example




## **J2EE/.NET - Average Number of Exceptions on Server Graph**

This graph displays the average number of code exceptions per method that were monitored during the selected time range.

<b>X-axis</b>	Elapsed time of the scenario run.
<b>Y-axis</b>	Number of events.
<b>Breakdown options</b>	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### **Example**




## **J2EE/.NET - Average Number of Timeouts in Transactions Graph**

This graph displays the average number of timeouts per method, transaction, or request that were monitored during the selected time range.

<b>X-axis</b>	Elapsed time since the scenario run.
<b>Y-axis</b>	Represents number of events.

<b>Breakdown options</b>	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




## **J2EE/.NET - Average Number of Timeouts on Server Graph**

This graph displays the average number of timeouts per method that were monitored during the selected time range.

<b>X-axis</b>	Elapsed time since the scenario run.
<b>Y-axis</b>	Number of events.
<b>Breakdown options</b>	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




## J2EE/.NET - Average Server Method Response Time Graph

This graph displays the average response time for the server side methods, computed as Total Method Response Time/Number of Method calls.

<b>X-axis</b>	Elapsed time since the scenario run.
<b>Y-axis</b>	Average response time (in seconds) per method.
<b>Breakdown options</b>	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>
<b>Note</b>	The method time does not include calls made from the method to other methods.
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




## J2EE/.NET - Method Calls per Second in Transactions Graph

This graph displays the number of completed sampled transactions during each second of a load test scenario run.

The number of transactions included in the sample is determined by the sampling percentage set in the Diagnostics Distribution dialog box in the Controller (**Diagnostics > Configuration**). For more information, refer to the *HP LoadRunner Controller User Guide*.

<b>X-axis</b>	Elapsed time.
<b>Y-axis</b>	Represents the number of completed sampled transactions per second.
<b>Breakdown options</b>	To break the displayed elements down further, see " <a href="#">Using the J2EE &amp; .NET Breakdown Options</a> " on page 1715.
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview"</a> on page 1708

### Example




## J2EE/.NET - Probes Metrics Graph

This graph displays performance metrics collected by HP Diagnostics probes. Metrics include JVM related data such as Heap usage and Garbage Collection, application server specific metrics, JDBC (Java Database Connectivity) metrics, and more.

<b>X-axis</b>	Elapsed time since the scenario run.
<b>Y-axis</b>	<p>Resource usage. The following probe metric data is provided for offline analysis:</p> <ul style="list-style-type: none"><li>• <b>HeapUsed</b></li><li>• <b>GC Collections/sec</b></li><li>• <b>GC time Spent in Collections</b></li></ul> <p>To include additional Probe metric data in offline Analysis, you use the Diagnostics configuration file, <b>etc./offline.xml</b>. For more information, see the <i>HP Diagnostics Server Installation and Administration Guide</i>.</p>
<b>Data Grouping</b>	By default, the data in the graph is grouped by Category Name (the Diagnostics metric category name) and Probe Name. As a result, the default format for the measurement name is the graph is: <Name of metric from Diagnostics (unit of metric)>:<Diagnostics metric category name>:<Probe name> If the measurement unit is a count, no unit name is displayed in parentheses.

<b>Important Information</b>	<p>By default, the following probe metric data is provided for offline analysis: <b>HeapUsed</b>, <b>GC Collections/sec</b>, and <b>GC time Spent in Collections</b>. To include additional Probe metric data in offline Analysis, you use the Diagnostics configuration file, <b>etc/offline.xml</b>. For more information, see the <i>HP Diagnostics LoadRunner and Performance Center-Diagnostics Integration Guide</i>.</p> <p>For example, for the following measurement name:</p> <ul style="list-style-type: none"><li>the name of the metric is <b>GC Time Spent in Collections</b>.</li><li>the value is measured as a percentage.</li><li>the metric category name is <b>GC</b>.</li><li>the Probe name is <b>MyJBossDev</b></li></ul> <p>In addition to the regular Analysis filter criteria, you can also filter and group by the Diagnostics metrics collector name and the host name.</p>
<b>Note</b>	You need to synchronize the operating system time settings on the Controller machine and the Diagnostics Servers to ensure accurate display of the elapsed scenario time in the Probe Metrics graph.
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




### **J2EE/.NET - Server Methods Calls per Second Graph**

This graph displays the number of completed sampled methods during each second of a load test scenario run.

<b>X-axis</b>	Elapsed time of the scenario run.
---------------	-----------------------------------

<b>Y-axis</b>	Number of completed sampled methods per second.
<b>Breakdown options</b>	"Using the J2EE & .NET Breakdown Options" on page 1715
<b>Note</b>	The number of methods included in the sample is determined by the sampling percentage set in the Diagnostics Distribution dialog box in the Controller ( <b>Diagnostics &gt; Configuration</b> ). For more information, refer to the <i>HP LoadRunner Controller User Guide</i> .
<b>See also</b>	"J2EE & .NET Diagnostics Graphs Overview" on page 1708

### Example




## J2EE/.NET - Server Requests per Second Graph

This graph displays the number of completed sampled requests during each second of a load test scenario run.

<b>X-axis</b>	Elapsed time of the scenario run.
<b>Y-axis</b>	Number of completed sampled requests per second.
<b>Breakdown options</b>	"Using the J2EE & .NET Breakdown Options" on page 1715

<b>Note</b>	The number of requests included in the sample is determined by the sampling percentage set in the Diagnostics Distribution dialog box in the Controller ( <b>Diagnostics &gt; Configuration</b> ). For more information, refer to the <i>HP LoadRunner Controller User Guide</i> .
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




## J2EE/.NET - Server Request Response Time Graph

This graph displays the server response time of requests that include steps that cause activity on the J2EE/.NET backend.

<b>X-axis</b>	Elapsed time of the scenario time.
<b>Y-axis</b>	Average time (in seconds) taken to perform each request.
<b>Breakdown options</b>	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>
<b>Note</b>	The reported times, measured from the point when the request reached the Web server to the point it left the Web server, include only the time that was spent in the J2EE/.NET backend.
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




### **J2EE/.NET - Server Request Time Spent in Element Graph**

This graph displays the server response time for the selected element (layer, class, or method) within each server request.

<b>Purpose</b>	The time is computed as Total Response Time/Total Number of Server Requests. For example, if a method was executed twice by an instance of server request A and once by another instance of the same server request, and it took three seconds for each execution, the average response time is 9/2, or 4.5 seconds. The server request time does not include the nested calls from within each server request.
<b>X-axis</b>	Elapsed time of the scenario run.
<b>Y-axis</b>	Average response time (in seconds) per element within the server request.
<b>Breakdown options</b>	<a href="#">"Using the J2EE &amp; .NET Breakdown Options" on page 1715</a>

<b>Filtering properties</b>	The display of the graph is determined by the Graph Properties selected when the graph is opened, as described:  <b>None</b> <ul style="list-style-type: none"><li>■ Time spent in each server request</li></ul> <b>Server request</b> <ul style="list-style-type: none"><li>■ Filtered by server request. Grouped by layer.</li></ul> <b>Server request and layer</b> <ul style="list-style-type: none"><li>■ Filtered by server request and layer. Grouped by class.</li></ul> <b>Server request, layer, and class</b> <ul style="list-style-type: none"><li>■ Filtered by server request, layer, and class. Grouped by method.</li></ul>
<b>Tips</b>	To obtain data for this graph, you must first install HP Diagnostics. Before you can view Diagnostics for J2EE & .NET data in a particular load test scenario, you need to configure the Diagnostics parameters for that scenario, as described in the <i>HP LoadRunner Controller User Guide</i> .
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview" on page 1708</a>

### Example




## J2EE/.NET - Transactions per Second Graph

This graph displays the number of completed sampled transactions during each second of a load test scenario run.

The number of transactions included in the sample is determined by the sampling percentage set in the Diagnostics Distribution dialog box in the Controller (**Diagnostics > Configuration**). For more information, refer to the *HP LoadRunner Controller User Guide*.

<b>X-axis</b>	Elapsed time.
<b>Y-axis</b>	Number of completed sampled transactions per second
<b>Breakdown options</b>	To break the displayed elements down further, see " <a href="#">Using the J2EE &amp; .NET Breakdown Options</a> " on page 1715.
<b>See also</b>	<a href="#">"J2EE &amp; .NET Diagnostics Graphs Overview"</a> on page 1708

### Example




## J2EE/.NET - Transaction Response Time Server Side Graph

This graph displays the transaction server response time of transactions that include steps that cause activity on the J2EE/.NET backend. The reported times, measured from the point when the transaction reached the Web server to the point it left the Web server, include only the time that was spent in the J2EE/.NET backend.

<b>X-axis</b>	Elapsed time.
---------------	---------------

<b>Y-axis</b>	Average response time (in seconds) of each transaction.
<b>Breakdown options</b>	"Using the J2EE & .NET Breakdown Options" on page 1715
<b>See also</b>	"J2EE & .NET Diagnostics Graphs Overview" on page 1708

### Example



## J2EE/.NET - Transaction Time Spent in Element Graph

This graph displays the server response time for the selected element (layer, class, or method) within each transaction.


<b>X-axis</b>	Elapsed time.
<b>Y-axis</b>	Average response time (in seconds) per element within the transaction.
<b>Breakdown options</b>	The display of graph data is determined by the graph properties selected when the graph was opened, as described in the following table: For information on filtering on graph data, see "Filtering Graph Data Overview" on page 1394.  You can break down the displayed elements. For more information, see "Using the J2EE & .NET Breakdown Options" on page 1715.
<b>Tips</b>	To obtain data for this graph, you must enable the J2EE & .NET Diagnostics module (from the Controller) before running the load test scenario.
<b>Note</b>	The time is computed as Total Response Time/Total Number of Transactions. For example, if a method was executed twice by an instance of transaction A and once by another instance of the same transaction, and it took three seconds for each execution, the average response time is 9/2, or 4.5 seconds. The transaction time does not include the nested calls from within each transaction.

**See also**

"J2EE & .NET Diagnostics Graphs Overview" on page 1708

"Filtering and Sorting Graph Data" on page 1394

**Example**



**Graph Data Display**

If you filter by these properties...	The graph data is displayed like this
None	Time spent in each transaction.
Transaction	Filtered by transaction. Grouped by layer.
Transaction and layer	Filtered by transaction and layer. Grouped by class.
Transaction, layer, and class	Filtered by transaction, layer, and class. Grouped by method.

## Troubleshooting and Limitations - Analysis

This section contains troubleshooting and limitations for Analysis.

## General

- Analysis API works only on x86 platforms. If you are using Visual Studio, define the platform as x86 in the Project options.
- WebSockets statistics graphs are not available in Analysis. To view this data, use the WebSockets online monitors under the Web Resources node, during the test run.
- When analyzing results from a load test in which the Web Vusers accesses the AUT through a proxy server, the **Time to First Buffer Breakdown** graph shows only zero values for Network Time and Server Time. This is because the "time to first buffer" metric is turned off when working behind a proxy, and the time values can only be calculated to the proxy server.
- Load results that contain transactions with the '@' or ',' characters may conflict with existing transactions. This is because Analysis attempts to replace those characters with the '\_', and if this results in a transaction name conflict, an error will occur.

**Workaround:** Avoid using the '@' and ',' characters in transaction names.

- Analysis may fail to load a result file created with an SQL 2012 database, when working with non-English operating systems. This occurs when the database server is not on the same machine as LoadRunner Analysis.

**Workaround:** Make sure the decimal separator (in the Analysis machine's Regional Settings) matches the decimal separator on the SQL server machine. Note: The *decimal separator* and *list separator* on the Analysis machine should be different .

- When the Analysis results consists of a large number of similar measurements, you may experience spikes in graphs, or an *Out of memory* message.

**Workaround:** For 64-bit Windows, make sure that you have 4 GB or more memory. For 32-bit Windows, Select **Start > Run**, and type msconfig. In the **Boot** tab, click **Advanced Options**. Select **Maximum memory** and set it to the maximum value.

- Analysis may fail to load a result file created with an SQL 2012 database, when working with non-English operating systems. This occurs when the database server is not on the same machine as LoadRunner Analysis.]

**Workaround:** Make sure the decimal separator (in the Analysis machine's Regional Settings) matches the decimal separator on the SQL server machine. **Note:** The decimal separator and list separator on the Analysis machine should be different .

## Microsoft SQL Server

If you are using Microsoft SQL Server 2000, you need to either migrate Analysis data, or upgrade to Microsoft SQL Server 2005. The following tasks describe how to perform the migrating and upgrading procedures:

### To migrate legacy Analysis data to a SQL 2005 server:

1. From the SQL Server Management Studio, using Object Explorer, connect to an instance of SQL Server Database Engine.

2. Expand Databases, right-click Analysis database, select Tasks\Copy Database.
3. Follow the instructions in the wizard.

**To upgrade SQL 2000 to SQL 2005:**

1. Uninstall SQL 2000.
2. Install SQL 2005.
3. Restore Analysis data from backup. ([http://msdn.microsoft.com/en-us/library/ms177429 \(SQL.90\).aspx](http://msdn.microsoft.com/en-us/library/ms177429(SQL.90).aspx))
  - If you are using your own policy in an MS SQL server, you may need to add your own account to the Analysis database template (in the <LR Installation>\bin\dat folder).
  - When exporting Analysis reports to MS Word, take into account that the content load may affect the table format within the document. The RTF format is recommended.
  - The following Analysis default settings have been modified: **Include Think Time** is disabled and **Display summary while generating complete data** is enabled.
  - There is a limitation with MS Access and SQL queries when filtering a large number of transactions (greater than 100).
  - Even after running the <Language> User Interface Pack, the Analysis UI data generated from the sample session (in the <LR Installation>\tutorial folder) will display in English. Filtering the graphs will fail.

**Workaround:** Re-generate the graphs and then the corresponding language from the <Language> User Interface Pack will display and filtering will work.

- The following Analysis default settings have been modified: **Include Think Time** is disabled and **Display summary while generating complete data** is enabled.
- There is a limitation with MS Access and SQL queries when filtering a large number of transactions (greater than 100).
- Even after running the <Language> User Interface Pack, the Analysis UI data generated from the sample session (in the <LR Installation>\tutorial folder) will display in English. Filtering the graphs will fail.

**Workaround:** Re-generate the graphs and then the corresponding language from the <Language> User Interface Pack will display and filtering will work.

# LoadRunner Guides and References

The following guides and references are available for LoadRunner.

Most of the guides are available through the LoadRunner Start menu. For complete access, use the LoadRunner online help from the product's **Help** menu and select the guide from the online version of the **LoadRunner Guides and References** page.

**Note:** To check for recent updates of any of the guides below, visit the HP Software Product Manuals Web site (<http://h20230.www2.hp.com/selfsolve/manuals>).

## Getting started

Reference	Description
"What's New in LoadRunner 12.00" on page 60	Describes the newest features in the latest version of LoadRunner. You can also access the <b>What's New</b> from the LoadRunner <b>Help</b> menu.
Product Movies	Click the link or select <b>Help &gt; Product Feature Movies</b> to view short movies that demonstrate the main product features.
Readme	Provides last-minute news and information about LoadRunner. For the latest readme file, use one of the following links: <ul style="list-style-type: none"><li>• HP Software Manuals Web site (<a href="http://support.openview.hp.com/selfsolve/document/KM00589225/binary/LoadRunner12.00_Readme.htm">http://support.openview.hp.com/selfsolve/document/KM00589225/binary/LoadRunner12.00_Readme.htm</a>)</li><li>• HP Live Network (HPLN) at <a href="https://hpln.hp.com/page/hp-loadrunner-1200-readme">https://hpln.hp.com/page/hp-loadrunner-1200-readme</a>.</li><li>• QR Code directly to the HPLN site.</li></ul>
Tutorial	The LoadRunner tutorial is a self-paced printable guide, designed to lead you through the process of load testing and familiarize you with the LoadRunner testing environment.



**LoadRunner PDF Guides** 

Guide	Description
LoadRunner User Guide (this guide)	Describes how to create and run LoadRunner scenarios using the LoadRunner Controller in a Windows environment. Also describes how to set up the server monitor environment and configure LoadRunner monitors for monitoring data generated during a scenario.
LoadRunner Installation Guide	Explains how to install LoadRunner and load generators, available on the DVD.
Monitors Best Practices Guide	Provides best practices for working with online monitors.
DFE Developers Guide	Describes how to work with DFEs. The DFE is a utility that converts one type of input into a standard output format and back again. This guide also provides access to the DFE extensions.

**API References**

Reference	Description
LoadRunner Function Reference	The HP LoadRunner Function Reference gives you online access to all of LoadRunner's API functions that you can use when creating Vuser scripts, along with examples of how to use the functions.
Analysis API Reference	This Analysis API set can be used for creating an unattended Analysis session or for custom extraction of data from the results of a test that ran under the Controller.

# Additional Components

You can install additional components that provide advanced features for working with LoadRunner. You install these components from the following locations:

- The **Additional Components** folder inside the root folder of the LoadRunner installation DVD.
- **HP Software Support Online (Help > HP Software Support Site)**. After logging in to the support site, search for "LR 12.00 Additional Components", and download the file that contains all the additional components. Unzip the file, and run the installation wizard for the additional component that you want to install.

The table below indicates which additional components are available, and where you should install each component:

Folder	Component	Description	Install on...
<b>Agent for Citrix Server</b>	Setup file	Installs the Citrix Agent which enhances VuGen's capabilities in identifying Citrix client objects during Citrix protocol record and replay. For installation instructions, see " <a href="#">Installing the Citrix Server Agent</a> " on page 1009.  The agent also enables you to use additional Citrix API functions. For details, see the <a href="#">LoadRunner Function Reference</a> .	Citrix Server
<b>Agent for Microsoft Terminal Server</b>	Setup file for MS Terminal Agent	Installs a utility that enhances the RDP protocol's recording mechanism in VuGen. For installation instructions, see " <a href="#">Installing the Microsoft Terminal Server Agent</a> " on page 1011.	RDP server
<b>Assembly Crawler for Analysis API</b>	Setup file for Assembly Crawler Console	Installs a command-line utility to build a .NET configuration file for a LoadRunner Analysis API application. For more information, open the <b>Analysis API Reference</b> from the <b>Start &gt; Documentation</b> menu (not available with VuGen Standalone).	LoadRunner Analysis machine
<b>HostID Generator</b>	Host ID Generator tool, licidgenerator.exe	Opens the Host ID Generator utility that displays the computer's Host ID. This is useful when requesting a license. For details, see " <a href="#">LoadRunner License Utility</a> " on page 1022.	LoadRunner Controller

Folder	Component	Description	Install on...
<b>HP Performance Validation SDK</b>	Configuration Builder Setup file	Installs the <b>Configuration Builder</b> which allows you to create a custom protocol. For more information, after the installation, open the <b>Configuration Builder</b> from the LoadRunner group and access the <b>Help</b> menu.	VuGen machine
<b>IDE Add-Ins</b>	Add-in setup files for common versions of Visual Studio	Installs add-ins for Visual Studio enabling you to create Vuser scripts in your standard development environment using the LoadRunner API. This integration also allows you to run the test directly from Visual Studio, to test its functionality. For details, see <a href="#">"Creating Scripts in External IDEs" on page 969</a> .	Visual Studio machine with VuGen
<b>IDE Add-Ins Dev</b>	Setup files for developer add-ins for Visual Studio 2010/ 2012 and Eclipse	Installs add-ins for Visual Studio or Eclipse, enabling you to create NUnit or JUnit tests in your standard development environment using the LoadRunner API. For details, see <a href="#">"Creating Scripts in External IDEs" on page 969</a> .	Visual Studio or Eclipse machine with VuGen
<b>LRTCPDump</b>	Command line executable for Windows and UNIX platforms	<p>Creates a trace file containing logs of TCP traffic over the network. This can be used as an alternative to Wireshark.</p> <p>For details, see <a href="#">"How to Create a Script by Analyzing Traffic" on page 860</a>.</p>	Any machine with WinPcap (see below)
<b>mobile RemoteAgent</b>	Executable files for several platforms	Starts the Mongoose Web server to provide mobile functionality. For details, see <a href="#">"How to Record and Analyze a Script for Mobile Applications" on page 707</a>	Mobile AUT backend server
<b>SAP Tools</b>	Executable and help files for SapSpy and VerifyScripting	<ul style="list-style-type: none"> <li><b>SAPGUI Spy.</b> Examines the hierarchy of GUI Scripting objects, on open windows of <b>SAPGUI Client for Windows</b>.</li> <li><b>SAPGUI Verify Scripting.</b> Verifies that the SAPGUI Scripting API is enabled.</li> </ul> <p>For details, see <a href="#">"How to Configure the SAP Environment" on page 782</a>.</p>	VuGen machine with SAPGUI client

Folder	Component	Description	Install on...
<b>Third Parties</b>	Source files	The folder contains the source code of some third party software components which are being used in LoadRunner. See the table below for information about some of these components.	
<b>Virtual Table Server</b>	Setup file	This installation runs the VTS setup through a wizard. For details, see " <a href="#">"Installing VTS" on page 1010.</a>	Any machine

## Third Party Components

Folder	Component	Description	Install on...
<b>MQTester</b>	Zip file containing setup file for MQTester	Installs OpenText MQTester for HP LoadRunner. MQTester integrates with LoadRunner to provide the capability to load-test and stress-test WebSphere MQ-based systems.	LoadRunner or Load Generator machine
<b>WinPcap</b>	Setup file	<p>Installs WinPcap, the Windows Packet Capture libraries, enabling you to capture network traffic into a file. This is useful for creating a Web Services or Mobile HTTP Vuser script from captured traffic. For details, see <a href="http://www.winpcap.org">http://www.winpcap.org</a>.</p> <p>This is to be used in conjunction with the additional component, LRTCPDump.</p>	Any machine