■ NetApp

Azure credentials

Set up and administration

NetApp September 11, 2022

This PDF was generated from https://docs.netapp.com/us-en/cloud-manager-setup-admin/concept-accounts-azure.html on September 11, 2022. Always check docs.netapp.com for the latest.

Table of Contents

Azure credentials			 	1
Azure credentials and permissions			 	1
Managing Azure credentials and subs	criptions for Clou	ıd Manager	 	3

Azure credentials

Azure credentials and permissions

Cloud Manager enables you to choose the Azure credentials to use when deploying Cloud Volumes ONTAP. You can deploy all of your Cloud Volumes ONTAP systems using the initial Azure credentials, or you can add additional credentials.

Initial Azure credentials

When you deploy a Connector from Cloud Manager, you need to use an Azure account or service principal that has permissions to deploy the Connector virtual machine. The required permissions are listed in the Connector deployment policy for Azure.

When Cloud Manager deploys the Connector virtual machine in Azure, it enables a system-assigned managed identity on virtual machine, creates a custom role, and assigns it to the virtual machine. The role provides Cloud Manager with permissions to manage resources and processes within that Azure subscription. Review how Cloud Manager uses the permissions.



Cloud Manager selects these Azure credentials by default when you create a new working environment for Cloud Volumes ONTAP:



Additional Azure subscriptions for a managed identity

The managed identity is associated with the subscription in which you launched the Connector. If you want to select a different Azure subscription, then you need to associate the managed identity with those subscriptions.

Additional Azure credentials

If you want to deploy Cloud Volumes ONTAP using different Azure credentials, then you must grant the required permissions by creating and setting up a service principal in Azure Active Directory for each Azure account. The following image shows two additional accounts, each set up with a service principal and custom role that provides permissions:







You would then add the account credentials to Cloud Manager by providing details about the AD service principal.

After you add another set of credentials, you can switch to them when creating a new working environment:



What about Marketplace deployments and on-prem deployments?

The sections above describe the recommended deployment method for the Connector, which is from NetApp Cloud Central. You can also deploy a Connector in Azure from the Azure Marketplace, and you can install the Connector on-premises.

If you use the Marketplace, permissions are provided in the same way. You just need to manually create and set up the managed identity for the Connector, and then provide permissions for any additional accounts.

For on-premises deployments, you can't set up a managed identity for the Connector, but you can provide permissions just like you would for additional accounts by using a service principal.

Managing Azure credentials and subscriptions for Cloud Manager

When you create a Cloud Volumes ONTAP system, you need to select the Azure credentials to use with that system. You also need to choose a Marketplace subscription, if you're using pay-as-you-go licensing. Follow the steps on this page if you need to use multiple Azure credentials or multiple Azure Marketplace subscriptions for Cloud Volumes ONTAP.

There are two ways to add additional Azure subscriptions and credentials in Cloud Manager.

- 1. Associate additional Azure subscriptions with the Azure managed identity.
- 2. If you want to deploy Cloud Volumes ONTAP using different Azure credentials, grant Azure permissions using a service principal and add its credentials to Cloud Manager.

Associating additional Azure subscriptions with a managed identity

Cloud Manager enables you to choose the Azure credentials and Azure subscription in which you want to deploy Cloud Volumes ONTAP. You can't select a different Azure subscription for the managed identity profile unless you associate the managed identity with those subscriptions.

About this task

A managed identity is the initial Azure account when you deploy a Connector from Cloud Manager. When you deployed the Connector, Cloud Manager created the Cloud Manager Operator role and assigned it to the Connector virtual machine.

Steps

- 1. Log in to the Azure portal.
- Open the Subscriptions service and then select the subscription in which you want to deploy Cloud Volumes ONTAP.
- 3. Click Access control (IAM).
 - a. Click Add > Add role assignment and then add the permissions:
 - Select the Cloud Manager Operator role.



Cloud Manager Operator is the default name provided in the Connector policy. If you chose a different name for the role, then select that name instead.

- Assign access to a Virtual Machine.
- Select the subscription in which the Connector virtual machine was created.
- Select the Connector virtual machine.
- Click Save.
- 4. Repeat these steps for additional subscriptions.

Result

When you create a new working environment, you should now have the ability to select from multiple Azure subscriptions for the managed identity profile.



Adding additional Azure credentials to Cloud Manager

When you deploy a Connector from Cloud Manager, Cloud Manager enables a system-assigned managed identity on the virtual machine that has the required permissions. Cloud Manager selects these Azure credentials by default when you create a new working environment for Cloud Volumes ONTAP.



An initial set of credentials isn't added if you manually installed the Connector software on an existing system. Learn about Azure credentials and permissions.

If you want to deploy Cloud Volumes ONTAP using *different* Azure credentials, then you must grant the required permissions by creating and setting up a service principal in Azure Active Directory for each Azure account. You can then add the new credentials to Cloud Manager.

Granting Azure permissions using a service principal

Cloud Manager needs permissions to perform actions in Azure. You can grant the required permissions to an Azure account by creating and setting up a service principal in Azure Active Directory and by obtaining the Azure credentials that Cloud Manager needs.

About this task

The following image depicts how Cloud Manager obtains permissions to perform operations in Azure. A service principal object, which is tied to one or more Azure subscriptions, represents Cloud Manager in Azure Active Directory and is assigned to a custom role that allows the required permissions.



Steps

- 1. Create an Azure Active Directory application.
- 2. Assign the application to a role.
- 3. Add Windows Azure Service Management API permissions.
- 4. Get the application ID and directory ID.
- 5. Create a client secret.

Creating an Azure Active Directory application

Create an Azure Active Directory (AD) application and service principal that Cloud Manager can use for role-based access control.

Before you begin

You must have the right permissions in Azure to create an Active Directory application and to assign the application to a role. For details, refer to Microsoft Azure Documentation: Required permissions.

Steps

1. From the Azure portal, open the **Azure Active Directory** service.



- 2. In the menu, click **App registrations**.
- 3. Click New registration.
- 4. Specify details about the application:
 - Name: Enter a name for the application.
 - Account type: Select an account type (any will work with Cloud Manager).
 - Redirect URI: You can leave this field blank.
- 5. Click Register.

Result

You've created the AD application and service principal.

Assigning the application to a role

You must bind the service principal to one or more Azure subscriptions and assign it the custom "OnCommand Cloud Manager Operator" role so Cloud Manager has permissions in Azure.

Steps

- 1. Create a custom role:
 - a. Copy the contents of the custom role permissions for the Connector and save them in a JSON file.
 - b. Modify the JSON file by adding Azure subscription IDs to the assignable scope.

You should add the ID for each Azure subscription from which users will create Cloud Volumes ONTAP systems.

Example

```
"AssignableScopes": [
"/subscriptions/d333af45-0d07-4154-943d-c25fbzzzzzzzz",
"/subscriptions/54b91999-b3e6-4599-908e-416e0zzzzzzzz",
"/subscriptions/398e471c-3b42-4ae7-9b59-ce5bbzzzzzzzz"
```

c. Use the JSON file to create a custom role in Azure.

The following steps describe how to create the role by using Bash in Azure Cloud Shell.

- Start Azure Cloud Shell and choose the Bash environment.
- Upload the JSON file.



• Enter the following Azure CLI command:

```
az role definition create --role-definition
Policy_for_Setup_As_Service_Azure.json
```

You should now have a custom role called Cloud Manager Operator that you can assign to the Connector virtual machine.

- 2. Assign the application to the role:
 - a. From the Azure portal, open the **Subscriptions** service.
 - b. Select the subscription.
 - c. Click Access control (IAM) > Add > Add role assignment.
 - d. In the Role tab, select the Cloud Manager Operator role and click Next.
 - e. In the **Members** tab, complete the following steps:
 - Keep User, group, or service principal selected.
 - Click Select members.



Search for the name of the application.

Here's an example:



- Select the application and click Select.
- Click Next.
- f. Click **Review + assign**.

The service principal now has the required Azure permissions to deploy the Connector.

If you want to deploy Cloud Volumes ONTAP from multiple Azure subscriptions, then you must bind the service principal to each of those subscriptions. Cloud Manager enables you to select the subscription that you want to use when deploying Cloud Volumes ONTAP.

Adding Windows Azure Service Management API permissions

The service principal must have "Windows Azure Service Management API" permissions.

- 1. In the Azure Active Directory service, click App registrations and select the application.
- 2. Click API permissions > Add a permission.
- 3. Under Microsoft APIs, select Azure Service Management.



4. Click Access Azure Service Management as organization users and then click Add permissions.



Getting the application ID and directory ID

When you add the Azure account to Cloud Manager, you need to provide the application (client) ID and the directory (tenant) ID for the application. Cloud Manager uses the IDs to programmatically sign in.

Steps

- 1. In the Azure Active Directory service, click App registrations and select the application.
- 2. Copy the Application (client) ID and the Directory (tenant) ID.



Creating a client secret

You need to create a client secret and then provide Cloud Manager with the value of the secret so Cloud Manager can use it to authenticate with Azure AD.

- 1. Open the Azure Active Directory service.
- 2. Click **App registrations** and select your application.
- 3. Click Certificates & secrets > New client secret.

- 4. Provide a description of the secret and a duration.
- 5. Click Add.
- 6. Copy the value of the client secret.

Client secrets

A secret string that the application uses to prove its identity when requesting a token. Also can be referred to as application password.



Result

Your service principal is now setup and you should have copied the application (client) ID, the directory (tenant) ID, and the value of the client secret. You need to enter this information in Cloud Manager when you add an Azure account.

Adding the credentials to Cloud Manager

After you provide an Azure account with the required permissions, you can add the credentials for that account to Cloud Manager. Completing this step enables you to launch Cloud Volumes ONTAP using different Azure credentials.

Before you get started

If you just created these credentials in your cloud provider, it might take a few minutes until they are available for use. Wait a few minutes before you add the credentials to Cloud Manager.

What you'll need

You need to create a Connector before you can change Cloud Manager settings. Learn how.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select Credentials.



- 2. Click **Add Credentials** and follow the steps in the wizard.
 - a. Credentials Location: Select Microsoft Azure > Connector.
 - b. **Define Credentials**: Enter information about the Azure Active Directory service principal that grants the required permissions:
 - Application (client) ID: See Getting the application ID and directory ID.
 - Directory (tenant) ID: See Getting the application ID and directory ID.
 - Client Secret: See Creating a client secret.
 - c. **Marketplace Subscription**: Associate a Marketplace subscription with these credentials by subscribing now or by selecting an existing subscription.

To pay for Cloud Volumes ONTAP at an hourly rate (PAYGO), these Azure credentials must be associated with a subscription from the Azure Marketplace.

d. Review: Confirm the details about the new credentials and click Add.

Result

You can now switch to different set of credentials from the Details and Credentials page when creating a new working environment



Manage existing credentials

Manage the Azure credentials that you've already added to Cloud Manager by associating a Marketplace subscription, editing credentials, and deleting them.

Associating an Azure Marketplace subscription to credentials

After you add your Azure credentials to Cloud Manager, you can associate an Azure Marketplace subscription to those credentials. The subscription enables you to create a pay-as-you-go Cloud Volumes ONTAP system, and to use other NetApp cloud services.

There are two scenarios in which you might associate an Azure Marketplace subscription after you've already added the credentials to Cloud Manager:

- You didn't associate a subscription when you initially added the credentials to Cloud Manager.
- You want to replace an existing Azure Marketplace subscription with a new subscription.

What you'll need

You need to create a Connector before you can change Cloud Manager settings. Learn how.

- 1. In the upper right of the Cloud Manager console, click the Settings icon, and select Credentials.
- 2. Click the action menu for a set of credentials and then select Associate Subscription.



3. Select a subscription from the down-down list or click **Add Subscription** and follow the steps to create a new subscription.

The following video starts from the context of the working environment wizard, but shows you the same workflow after you click **Add Subscription**:

▶ https://docs.netapp.com/us-en/cloud-manager-setup-admin//media/video_subscribing_azure.mp4

(video)

Editing credentials

Edit your Azure credentials in Cloud Manager by modifying the details about your Azure service credentials. For example, you might need to update the client secret if a new secret was created for the service principal application.

Steps

- 1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Credentials**.
- 2. Click the action menu for a set of credentials and then select **Edit Credentials**.
- 3. Make the required changes and then click **Apply**.

Deleting credentials

If you no longer need a set of credentials, you can delete them from Cloud Manager. You can only delete credentials that aren't associated with a working environment.

- 1. In the upper right of the Cloud Manager console, click the Settings icon, and select Credentials.
- 2. Click the action menu for a set of credentials and then select **Delete Credentials**.
- 3. Click Delete to confirm.

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.