页码,1/5 Lazy Foo' Productions

Lazy Foo' Productions

FAQs Tutorials Donations News Games Articles Contact

Albergo del Sedile Matera Hotel Design - 4 stelle all'ingresso dei due Powerful .Net Decompiler C#, VB.Net, Sassi-offerte

Spices.Decompiler Delphi, C++, J#

Ads by Google

Setting up SDL Extension Libraries in Code::Blocks

Last Updated 12/09/07

In this tutorial you're going to learn to set up SDL_image. If you know how to set up this extension, you can set any of them up.

SDL_image is located on this page.

1)Scroll down to the Binary section and download the Windows development library

Binary:

Linux

SDL image-1.2.4-1.i386.rpm

SDL image-1.2.4-1.ppc.rpm

SDL image-devel-1.2.4-1.i386.rpm

SDL image-devel-1.2.4-1.ppc.rpm

Win32

SDL image-1.2.4-win32.zip

SDL image-devel-1.2.4-VC6.zip \leftarrow

MacOS X

SDL image-1.2.4.pkg.tar.gz

Every extension libary has 3 essential parts:


- 1. The header file.
- 2. The lib file.
- 3. The *.dll file(s)

They're all set up pretty much the same way no matter which extension

you're setting up.


Open up the zip archive and there should be a folder inside. Open the folder and it'll contain 2 subfolders.

- 2)First, open the include subfolder in the archive and extract the header file inside to the SDL subfolder inside of the Code::Blocks include folder. It should be at C:\Program Files\CodeBlocks\include\SDL.
- 3)Next extract the lib file that's inside of lib subfolder of the archive to the Code::Blocks lib folder. The Code::Blocks lib folder should be at C:\Program Files\CodeBlocks\lib.
- 4)Next extract the *.dll file(s) located in the lib subfolder of the archive to the Code::Blocks bin folder. It should be at C:\Program Files\CodeBlocks\bin.
- 5)Now extract the *.dll file(s) to C:\WINDOWS\SYSTEM32. This is so whenever you make an SDL extension app, the program will be able to find the *.dll file(s) even if they're not in the same directory as the *.exe.
- 6) Now open up your SDL workspace and go to the compiler options.



For those of you using the nightly build, it's under project -> build options.

7) Then under the linker options tab, click the add button in the Link libraries field.



9)To use SDL_image make sure to include the header file.

#include "SDL/SDL_image.h"

```
If you were setting up SDL_ttf you'd put

#include "SDL/SDL_ttf.h"

If you were setting up SDL_mixer you'd put

#include "SDL/SDL_mixer.h"

etc, etc.

Now the extension library is all set up.
```

```
Now you can use SDL_image functions.
```

The main one you want to know about is IMG_Load().

```
SDL_Surface *load_image( std::string filename )
{
    //The image that's loaded
    SDL_Surface* loadedImage = NULL;

    //The optimized image that will be used
    SDL_Surface* optimizedImage = NULL;

    //Load the image using SDL_image
    loadedImage = IMG_Load( filename.c_str() );

    //If the image loaded
    if( loadedImage != NULL )
    {
        //Create an optimized image
        optimizedImage = SDL_DisplayFormat( loadedImage );

        //Free the old image
        SDL_FreeSurface( loadedImage );

        //Return the optimized image
        return optimizedImage;
}
```

Here is a revised version of the image loading function from the previous tutorial. As you can see IMG_Load() functions exactly the same as SDL_LoadBMP(), but there's one big exception: IMG_Load() can load BMP, PNM, XPM, LBM, PCX, GIF, JPEG, TGA and PNG files.

From this tutorial on, PNG image files will be the primary image format used. PNGs have excellent lossless compression.

Download the media and source code for this tutorial here.

I highly recommend that you download the documentation for SDL_image and keep it handy.

It can be found here.

THUM
TruBurst2
Temperature Humidity USB Monitor
Environmental Data Logger
Intelligent, Fully Pneumatic Burst Strength
Tester
Ads by Google

News FAQs Games Tutorials Articles Contact Donations

Copyright Lazy Foo' Productions 2004-2008