Common Lisp Webdriver Client

Table of Contents

1	Introduction	1
2	Usage	2
	2.1 Sessions	2
	2.2 Capabilities	
	2.2.1 alwaysMatch	4
	2.2.2 firstMatch	
	2.2.3 Combining alwaysMatch and firstMatch	4
	2.2.4 List of capabilities	5
	2.2.5 Vendor-specific capabilities	5
	2.3 Actions	5
3	Installation	7
4	Utils	8
	4.1 Interactive session	8
	4.2 Utils API conventions	
	4.3 Waiting for the reaction	
	4.4 Running tests	
5	API	10
	5.1 WEBDRIVER-CLIENT package	10
	5.2 WEBDRIVER-CLIENT-UTILS package	
6	Index	21

1 Introduction

CL Webdriver Client is client library for WebDriver.

WebDriver is a remote control interface that enables introspection and control of user agents. It provides a platform- and language-neutral wire protocol as a way for out-of-process programs to remotely instruct the behavior of web browsers.

Provided is a set of interfaces to discover and manipulate DOM elements in web documents and to control the behavior of a user agent. It is primarily intended to allow web authors to write tests that automate a user agent from a separate controlling process, but may also be used in such a way as to allow in-browser scripts to control a — possibly separate — browser.

See W3C Webdriver spec (https://www.w3.org/TR/webdriver).

2 Usage

```
;; see examples/*.lisp and t/*.lisp
(in-package :cl-user)
(eval-when (:compile-toplevel :load-toplevel :execute)
  (ql:quickload :cl-webdriver-client))
(defpackage go-test
  (:use :cl :webdriver-client))
(in-package :go-test)
(defparameter *code* "
package main
import \"fmt\"
func main() {
   fmt.Print(\"Hello WebDriver!\")
}")
(with-session ()
  (setf (url) "http://play.golang.org/?simple=1")
  (let ((elem (find-element "#code" :by :css-selector)))
    (element-clear elem)
    (element-send-keys elem *code*))
  (let ((btn (find-element "#run")))
    (element-click btn))
  (loop
     with div = (find-element "#output")
     for ouput = (element-text div)
     while (equal ouput "Waiting for remote server...")
     do (sleep 0.1)
     finally (print ouput)))
```

2.1 Sessions

A session is equivalent to a single instantiation of a particular user agent, including all its child browsers. WebDriver gives each session a unique session ID that can be used to differentiate one session from another, allowing multiple user agents to be controlled from a single HTTP server, and allowing sessions to be routed via a multiplexer (known as an intermediary node).

A WebDriver session represents the connection between a local end and a specific remote end.

A session is started when a New Session is invoked. It is an error to send any commands before starting a session, or to continue to send commands after the session has been closed.

Maintaining session continuity between commands to the remote end requires passing a session ID.

A session is torn down at some later point; either explicitly by invoking Delete Session, or implicitly when Close Window is called at the last remaining top-level browsing context.

An intermediary node will maintain an associated session for each active session. This is the session on the upstream neighbor that is created when the intermediary node executes the New Session command. Closing a session on an intermediary node will also close the session of the associated session.

All commands, except New Session and Status, have an associated current session, which is the session in which that command will run.

Use [START-INTERACTIVE-SESSION], page 12 function to start an interactive session, and [WITH-SESSION], page 12 macro to evaluate WebDriver code in the context of a session.

2.2 Capabilities

WebDriver capabilities are used to communicate the features supported by a session. A client may also use capabilities to define which features it requires the driver to satisfy when creating a new session.

When a WebDriver session is created it returns a set of capabilities describing the negotiated, effective capabilities of the session. Some of the capabilities included in this set are standard and shared between all browsers, but the set may also contain browser-specific capabilities and these are always prefixed. Capabilities negotiation

Capabilities can be used to require a driver that supports a certain subset of features. This can be used to require certain browser features, such as the ability to resize the window dimensions, but is also used in distributed environments to select a particular browser configuration from a matrix of choices.

Selecting a particular web browser or platform only makes sense when you use a remote WebDriver. In this case the client makes contact with WebDriver through one or more intermediary nodes which negotiates which driver to return to you based on the capabilities it receives.

The capabilities object is a selection mechanism that limits which driver configurations the server will return. If you request a Firefox instance using browserName and Firefox is not installed on the remote, or macOS from a remote that only supports Linux, you may be out of luck. But occasionally you may not care which specific operating system or web browser your session has: you just want a session that has some capability.

The selection process, or the capabilities negotiation, is done through alwaysMatch and firstMatch.

In *CL-WEBDRIVER-CLIENT* capabilities are created using [MAKE-CAPABILITIES], page 11. The key argument *:always-match* should be the 'alwaysMatch' capabilities as an association list. The key argument *:first-match* are the 'firstMatch' capabilities, a list of association lists.

Also, capabilities are constructed from arguments in [MAKE-SESSION], page 12 and [WITH-SESSION], page 12.

2.2.1 alwaysMatch

As the name suggests, capabilities described inside the alwaysMatch capabilities object are features you require the session to have. If the server can not provide what features you require, it will fail.

If for example you ask for Firefox version 62 on a system that only has 60 installed, the session creation will fail:

2.2.2 firstMatch

The firstMatch field accepts an array of capabilities objects which will be matched in turn until one matches what the server can provide, or it will fail.

This can be useful when you want a driver that runs on macOS or Linux, but not Windows:

```
(make-capabilities
  :first-match (list
       '((:platform-name . "macos"))
       '((:platform-name . "linux"))))
```

2.2.3 Combining alwaysMatch and firstMatch

firstMatch can of course be combined with alwaysMatch to narrow down the selection. If for example you a driver that runs on macOS or Linux but it has to be Firefox:

```
(make-capabilities
    :always-match '((:browser-name . "firefox"))
    :first-match (list
        '((:platform-name . "macos"))
        '((:platform-name . "linux"))))
```

The previous example is exactly equivalent to putting the Firefox requirement in each firstMatch arm:

```
(make-capabilities
    :first-match (list
        '((:browser-name . "firefox") (:platform-name . "macos"))
        '((:browser-name . "firefox") (:platform-name . "linux"))))
```

Which you choose of the two preceding examples is not important, but it can matter when pass along browser configuration. To avoid unnecessarily repeating data, such as profiles, it is advisable to make use of alwaysMatch so that this data is only transmitted across the wire once:

```
(make-capabilities
  :always-match '((:browser-name . "firefox")
```

2.2.4 List of capabilities

- :browser-name a string. The name of the browser to use. e.g. "chrome", "firefox".
- :browser-version a string. The browser version required.
- \bullet :platform-name a string. Identifies the operating system of the endpoint node. e.g. 'Linux', 'Windows'.
- :accept-insecure-certs a boolean. The acceptInsecureCerts capability communicates whether expired or invalid TLS certificates are checked when navigating. If the capability is false, an insecure certificate error will be returned as navigation encounters domains with certificate problems. Otherwise, self-signed or otherwise invalid certificates will be implicitly trusted by the browser on navigation. The capability has effect for the lifetime of the session.
- :page-load-strategy a string.
- :proxy object. Defines the current session's proxy configuration (https://www.w3.org/TR/webdriver1/#dfn-proxy-configuration).
- :set-window-rect boolean. Indicates whether the remote end supports all of the commands in Resizing and Positioning Windows (https://www.w3.org/TR/webdriver1/#resizing-and-positioning-windows).
- :timeouts object. Describes the timeouts (https://www.w3.org/TR/webdriver1/#dfn-timeouts) imposed on certain session operations.
- :unhandled-prompt-behaviour string. Describes the current session's user prompt handler.

Reference: https://www.w3.org/TR/webdriver1/#capabilities.

2.2.5 Vendor-specific capabilities

In addition to the standard capabilities WebDriver allows third-parties to extend the set of capabilities to match their needs. Browser vendors and suppliers of drivers typically use extension capabilities to provide configuration to the browser, but they can also be used by intermediaries for arbitrary blobs of information.

You can use [CHROME-CAPABILITIES], page 15 and [FIREFOX-CAPABILITIES], page 15 for these.

2.3 Actions

The Actions API provides a low-level interface for providing virtualised device input to the web browser. Conceptually, the Actions commands divide time into a series of ticks.

The local end sends a series of actions which correspond to the change in state, if any, of each input device during each tick. For example, pressing a key is represented by an action sequence consisting of a single key input device and two ticks, the first containing a keyDown action, and the second a keyUp action, whereas a pinch-zoom input is represented by an action sequence consisting of three ticks and two pointer input devices of type touch, each performing a sequence of actions pointerDown, followed by pointerMove, and then pointerUp.

See https://www.w3.org/TR/webdriver/#actions for the whole explanation.

To perform actions in *cl-webdriver-client* use [PERFORM-ACTIONS], page 13. That function implements a little language, with the following syntax:

Syntax:

```
actions ::= ({actions-input-source}*)
actions-input-source ::= (input-source-type {action}*)
input-source-type ::= :none | :pointer | :mouse | :pen | :touch | :key
action ::= pause | pointer-move | pointer-down | pointer-up | key-down | key-up
pause ::= (:pause duration)
pointer-move ::= (:pointer-move x y)
pointer-down ::= (:pointer-down button-number)
pointer-up ::= (:pointer-up button-number)
key-down ::= (:key-down key)
key-up ::= (:key-up key)
```

Arguments and values:

- actions—a list of actions-input-sources. One list for each type of input source that wants to be used.
- actions-input-source—a list. Specifies the list of actions to perform for a particular input source.
- duration—an integer. The time to pause in milliseconds.
- key—a string. A string with the character (e.g. "a"). Use [KEY], page 13 for entering special characters.
- button-number—an integer greater than or equal to 0.
- x—an integer. Horizontal screen coordinate.
- y—an integer. Vertical screen coordinate.

Examples:

3 Installation

```
git clone https://github.com/copyleft/cl-webdriver-client ~/quicklisp/local-projects/(ql:quickload :cl-webdriver-client)

You need a running instance of selenium-server-standalone.

[Download](http://www.seleniumhq.org/download/) it and run:

curl -LO https://goo.gl/SP94ZB -o selenium-server-standalone.jar
java -jar selenium-server-standalone.jar
```

4 Utils

There is a :webdriver-client-utils package which should reduce boilerplate. For example:

4.1 Interactive session

You can just start the session and control it from your repl:

```
(in-package :my-test)
(start-interactive-session)
(setf (url) "http://google.com")
(send-keys "cl-webdriver-client")
(send-keys (key :enter))
(classlist "#slim_appbar") ; prints ("ab_tnav_wrp")
(stop-interactive-session)
```

4.2 Utils API conventions

```
If utility function needs an element to work on it defaults to '(active-element)'.

(click); click on the current active element.

You can also pass a css selector as a last parameter.

(print (id "#submit")); print id the of matched element

(assert (= (first (classlist "div")) "first-div-ever"))

To change default element you can:

(setf webdriver-client-utils:*default-element-func* (lambda () (find-element "input[ty
```

Chapter 4: Utils 9

4.3 Waiting for the reaction

Often you need to wait for some action to be done. For example if you do a (click) on the button to load search results, you need to wait them to load.

```
(wait-for ".search-result" :timeout 10) ; wait 10 seconds
Timeout defaults to 30 seconds. You can globally change it:
   (setf webdriver-client-utils:*timeout* 3)
```

4.4 Running tests

REPL

```
(ql:quickload '(:cl-selenium :prove))
(setf prove:*enable-colors* nil)
(prove:run :cl-webdriver-client-test)
```

Shell

sh
./test.sh

5 API

5.1 WEBDRIVER-CLIENT package

WEBDRIVER-CLIENT [PACKAGE]

This package exports functions for working with Selenium WebDriver.

For documentation see:

- https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol
- https://www.w3.org/TR/webdriver1

External definitions

Uncategorized

LOGS (type &key (session *session*)) [WEBDRIVER-CLIENT]

Return the logs of a particular TYPE.

See: [LOG-TYPES], page 10.

NO-SUCH-ELEMENT-ERROR

[WEBDRIVER-CLIENT]

Error signaled when no such element is found.

Class precedence list: no-such-element-error, find-error, error, serious-condition, condition, t

MOUSE-MOVE-TO (x y & key element (session *session*)) [WEBDRIVER-CLIENT] Move the mouse by an offset of the specificed element. If no element is specified, the move is relative to the current mouse cursor. If an element is provided but no offset, the mouse will be moved to the center of the element. If the element is not visible, it will be scrolled into view.

 $See: \ https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol\#sessionsessionidmoveto$

ELEMENT-ID (sb-pcl::object)

[WEBDRIVER-CLIENT]

MOUSE-CLICK (button & key (session *session*))

[WEBDRIVER-CLIENT]

Click any mouse button (at the coordinates set by the last moveto command). Note that calling this command after calling buttondown and before calling button up (or any out-of-order interactions sequence) will yield undefined behaviour).

See: https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol#sessionsessionidclick

LOG-TYPES (&key (session *session*))

[WEBDRIVER-CLIENT]

Return the types of logs supported by the WebDriver.

- browser: Javascript console logs from the browser.
- client: Logs from the client side implementation of the WebDriver protocol (e.g. the

Java bindings).

- driver: Logs from the internals of the driver (e.g. FirefoxDriver internals).

- performance: Logs relating to the performance characteristics of the page under test (e.g. resource load timings).

- server: Logs from within the selenium server.

See: https://github.com/SeleniumHQ/selenium/wiki/Logging.

MAKE-CAPABILITIES (&key ((:always-match

[WEBDRIVER-CLIENT]

#:always-match) nil) ((:first-match #:first-match) nil))

WEBDRIVER-STATUS nil

[WEBDRIVER-CLIENT]

Get WebDriver status information

Navigation

BACK (&key (session *session*))

[WEBDRIVER-CLIENT]

This command causes the browser to traverse one step backward in the joint session history of the current top-level browsing context. This is equivalent to pressing the back button in the browser chrome or invoking window.history.back.

Category: Navigation

See: https://www.w3.org/TR/webdriver1/#dfn-back.

PAGE-SOURCE (&key (session *session*))

[WEBDRIVER-CLIENT]

Returns a string serialization of the DOM of the current browsing context active document.

Category: Navigation

See: https://www.w3.org/TR/webdriver1/#get-page-source

PAGE-TITLE (&key (session *session*))

[WEBDRIVER-CLIENT]

This command returns the document title of the current top-level browsing context, equivalent to calling document.title.

Category: Navigation

See: https://www.w3.org/TR/webdriver2/#get-title.

REFRESH (&key (session *session*))

[WEBDRIVER-CLIENT]

Refresh the current page.

Category: Navigation

SWITCH-TO-FRAME (id & key (session *session*))

[WEBDRIVER-CLIENT]

Change focus to another frame on the page. If the frame id is null, the server should switch to the page's default content.

In the context of a web browser, a frame is a part of a web page or browser window which displays content independent of its container, with the ability to load content

independently.

Category: Navigation

See: https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol#

sessionsessionidframe.

See: https://en.wikipedia.org/wiki/Frame_(World_Wide_Web) .

URL (&key (session *session*))

[WEBDRIVER-CLIENT]

Get the current url in session.

Category: Navigation

See: https://www.w3.org/TR/webdriver1/#dfn-get-current-url.

Session

START-INTERACTIVE-SESSION (&optional capabilities) [WEBDRIVER-CLIENT]

Start an interactive session. Use this to interact with Selenium driver from a REPL.

Category: Session

See: [MAKE-SESSION], page 12

WITH-SESSION (capabilities &body body) [WEBDRIVER-CLIENT]

Execute BODY inside a Selenium session.

Category: Session

See: [MAKE-SESSION], page 12

Make SESSION the current session.

Category: Session

USE-SESSION (session)

STOP-INTERACTIVE-SESSION nil

[WEBDRIVER-CLIENT]

Stop an interactive session.

Category: Session

MAKE-SESSION (capabilities)

[WEBDRIVER-CLIENT]

[WEBDRIVER-CLIENT]

Creates a new WebDriver session with the endpoint node. If the creation fails, a session not created error is returned.

CAPABILITIES are the capabilities to negotate for the new session. If it is NIL, then [*DEFAULT-CAPABILITIES*], page 15 are used. If it is a list, then it is use as parameters for [MAKE-CAPABILITIES], page 11 to build a new CAPABILITIES object. Otherwise, it is assumed to be a CAPABILITIES object.

Category: Session

See: https://www.w3.org/TR/webdriver1/#new-session. See: https://www.w3.org/TR/webdriver1/#capabilities.

DELETE-SESSION (session)

[WEBDRIVER-CLIENT]

Delete the WebDriver SESSION.

Category: Session

Screen capture

SCREENSHOT (&key (session *session*))

[WEBDRIVER-CLIENT]

Screenshots are a mechanism for providing additional visual diagnostic information. They work by dumping a snapshot of the initial viewport's framebuffer as a lossless PNG image. It is returned to the local end as a Base64 encoded string.

Category: Screen capture

See: https://www.w3.org/TR/webdriver2/#screen-capture.

ELEMENT-SCREENSHOT (element & key (session

[WEBDRIVER-CLIENT]

session))

The Take *Element* Screenshot command takes a screenshot of the visible region encompassed by the bounding rectangle of an *element*. If given a parameter argument scroll that evaluates to false, the *element* will not be scrolled into view.

Category: Screen capture

See: https://www.w3.org/TR/webdriver1/#take-element-screenshot.

Actions

KEY (key)

[WEBDRIVER-CLIENT]

Returns a string with KEY's codepoint.

Category: Actions

See: https://www.w3.org/TR/webdriver/#keyboard-actions

PERFORM-ACTIONS (actions & optional (session

[WEBDRIVER-CLIENT]

session))

The Actions API provides a low-level interface for providing virtualised device input to the web browser.

Conceptually, the *Actions* commands divide time into a series of ticks. The local end sends a series of *actions* which correspond to the change in state, if any, of each input device during each tick. For example, pressing a key is represented by an action sequence consisting of a single key input device and two ticks, the first containing a keyDown action, and the second a keyUp action, whereas a pinch-zoom input is represented by an action sequence consisting of three ticks and two pointer input devices of type touch, each performing a sequence of *actions* pointerDown, followed by pointerMove, and then pointerUp.

Category: Actions

See: https://www.w3.org/TR/webdriver/#actions

User prompts

ACCEPT-ALERT (&key (session *session*)) [WEBDRIVER-CLIENT]
Accept Alert.

Category: User prompts

See: https://www.w3.org/TR/webdriver1/#dfn-accept-alert

ALERT-TEXT (&key (session *session*)) [WEBDRIVER-CLIENT]
Get Alert Text.

Category: User prompts

See: https://www.w3.org/TR/webdriver1/#get-alert-text

DISMISS-ALERT (&key (session *session*)) [WEBDRIVER-CLIENT]

The Dismiss Alert command dismisses a simple dialog if present. A request to dismiss an alert user prompt, which may not necessarily have a dismiss button, has the same effect as accepting it.

Category: User prompts

See: https://www.w3.org/TR/webdriver1/#dismiss-alert

Document handling

EXECUTE-SCRIPT (script args &key (session *session*)) [WEBDRIVER-CLIENT] Inject a snippet of JavaScript into the page for execution in the context of the currently selected frame. The executed script is assumed to be synchronous and the result of evaluating the script is returned to the client.

The *script* argument defines the *script* to execute in the form of a function body. The value returned by that function will be returned to the client. The function will be invoked with the provided *args* array and the values may be accessed via the arguments object in the order specified.

Arguments may be any JSON-primitive, array, or JSON object. JSON objects that define a WebElement reference will be converted to the corresponding DOM element. Likewise, any WebElements in the *script* result will be returned to the client as WebElement JSON objects.

Category: Document handling

See: https://www.w3.org/TR/webdriver1/#executing-script.

Capabilities

MERGE-CAPABILITIES (cap1 cap2)

[WEBDRIVER-CLIENT]

Merge two capabilities

Category: Capabilities

CHROME-CAPABILITIES (&rest options)

[WEBDRIVER-CLIENT]

Specifies Chrome specific capabilities.

Category: Capabilities

https://chromedriver.chromium.org/capabilities#h.p_ID_102

FIREFOX-CAPABILITIES (&rest options)

[WEBDRIVER-CLIENT]

Specify capabilities for Firefox browser.

Example usage:

(firefox-capabilities :args #("-headless"))

Category: Capabilities

See: https://developer.mozilla.org/en-US/docs/Web/WebDriver/

Capabilities/firefoxOptions

DEFAULT-CAPABILITIES

[WEBDRIVER-CLIENT]

The default capabilities.

Category: Capabilities

Cookies

DELETE-ALL-COOKIES (&key (session *session*))

[WEBDRIVER-CLIENT]

Deletes all cookies

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#delete-all-cookies

MAKE-COOKIE (name value & key path domain secure

[WEBDRIVER-CLIENT]

expiry)

Create a cookie object.

Category: Cookies

DELETE-COOKIE (cookie-name & key (session *session*)) [WEBDRIVER-CLIENT]

Delete the cookie with name COOKIE-NAME.

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#delete-cookie

FIND-COOKIE (cookie-name & key (session *session*)) [WEBDRIVER-CLIENT]

Retrieve the cookie with name COOKIE-NAME.

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#get-named-cookie

COOKIE

[WEBDRIVER-CLIENT]

A cookie is described in [RFC6265] by a name-value pair holding the cookie's data, followed by zero or more attribute-value pairs describing its characteristics.

Category: Cookies

Class precedence list: cookie, standard-object, t

Slots:

• name — initarg: :name
The name of the cookie

• value — initarg: :value

The cookie value

• path — initarg: :path

The cookie path. Defaults to '/' if omitted when adding a cookie.

• domain — initarg: :domain

The domain the cookie is visible to. Defaults to the current browsing context's active document's URL domain if omitted when adding a cookie.

• secure — initarg: :secure

Whether the cookie is a secure cookie. Defaults to false if omitted when adding a cookie.

• http-only — initarg: :http-only

Whether the cookie is an HTTP only cookie. Defaults to false if omitted when adding a cookie.

• expiry — initarg: :expiry

When the cookie expires, specified in seconds since Unix Epoch. Must not be set if omitted when adding a cookie.

COOKIE (&key (session *session*))

[WEBDRIVER-CLIENT]

Retrieve all cookies visible to the current page.

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#get-all-cookies.

 $See: \ \texttt{https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol\#} \\$

sessionsessionidcookie.

Elements

ACTIVE-ELEMENT (&key (session *session*))

[WEBDRIVER-CLIENT]

Return the active element of the current browsing context's document.

The active element is the Element within the DOM that currently has focus.

If there's no active element, an error is signaled.

Category: Elements

See: https://www.w3.org/TR/webdriver2/#get-active-element.

See: https://developer.mozilla.org/en-US/docs/Web/API/Document/

activeElement.

FIND-ELEMENTS (value & key (by :css-selector) (session [WEBDRIVER-CLIENT] *session*))

Find elements that match VALUE using location strategy in BY.

Category: Elements

See [FIND-ELEMENT], page 18.

See https://www.w3.org/TR/webdriver1/#find-elements.

ELEMENT-DISPLAYED (element & key (session *session*)) [WEBDRIVER-CLIENT] Returns if ELEMENT is visible.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#element-displayedness.

ELEMENT-ATTRIBUTE (element name & key (session [WEBDRIVER-CLIENT] *session*))

Return the *ELEMENT*'s attribute named *NAME*.

Category: Elements

ELEMENT-ENABLED (element & key (session *session*)) [WEBDRIVER-CLIENT] Returns if ELEMENT is enabled.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#is-element-enabled.

ELEMENT-RECT (element & key (session *session*)) [WEBDRIVER-CLIENT]

The Get *Element* Rect command returns the dimensions and coordinates of the given web *element*. The returned value is a dictionary with the following members:

Х

X axis position of the top-left corner of the web *element* relative to the current browsing context's document *element* in CSS pixels.

у

Y axis position of the top-left corner of the web *element* relative to the current browsing context's document *element* in CSS pixels.

height

Height of the web element's bounding rectangle in CSS pixels.

width

Width of the web *element's* bounding rectangle in CSS pixels.

Category: Elements

ELEMENT-TEXT (element &key (session *session*)) [WEBDRIVER-CLIENT]

The Get *Element* Text command intends to return an *element*'s text "as rendered". An *element*'s rendered text is also used for locating a elements by their link text and partial link text.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#get-element-text.

ELEMENT-TAGNAME (element & key (session *session*)) [WEBDRIVER-CLIENT] Return the ELEMENT's tag name.

Category: Elements

FIND-ELEMENT (value & key (by :css-selector) (session [WEBDRIVER-CLIENT] *session*))

The Find Element command is used to find an element in the current browsing context that can be used as the web element context for future element-centric commands.

For example, consider this pseudo code which retrieves an element with the #tore-move ID and uses this as the argument for a script it injects to remove it from the HTML document:

let body (undefined) [=], page (undefined) session.find.css("#toremove"); session.execute("arguments[0].remove()", [body]);

The BY parameter represents the element location strategy.

It can be one of:

- :id : Finds element by id.
- :class-name : Finds element by class name.
- :css-selector : Returns element that matches css selector.
- : link-text : Returns element that matches <a> element text.
- :partial-link-text: Returns element that matches <a> element text partially.
- :tag-name: Returns element that matches tag name.
- :xpath: Returns element that matches the XPath expression.

If result is empty, a \langle undefined \rangle [HANDLE-FIND-ERROR], page \langle undefined \rangle is signaled.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#dfn-find-element.

Element interaction

ELEMENT-CLEAR (element & key (session *session*)) [WEBDRIVER-CLIENT] Clear the contents of ELEMENT (for example, a form field element).

Category: Element interaction

See: https://www.w3.org/TR/webdriver1/#dfn-element-clear.

ELEMENT-CLICK (element & key (session *session*)) [WEBDRIVER-CLIENT]

The Element Click command scrolls into view the element if it is not already pointerinteractable, and clicks its in-view center point.

If the element's center point is obscured by another element, an element click intercepted error is returned. If the element is outside the viewport, an element not interactable error is returned.

Category: Element interaction

See: https://www.w3.org/TR/webdriver1/#element-click.

ELEMENT-SEND-KEYS (element keys & key (session *session*))

[WEBDRIVER-CLIENT]

The *Element Send Keys* command scrolls into view the form control *element* and then sends the provided *keys* to the *element*. In case the *element* is not keyboard-interactable, an *element* not interactable error is returned.

KEYS should be a string.

Category: Element interaction

See: https://www.w3.org/TR/webdriver1/#element-send-keys.

Windows

CLOSE-CURRENT-WINDOW (&key (session *session*))

[WEBDRIVER-CLIENT]

Close the current window.

Category: Windows

5.2 WEBDRIVER-CLIENT-UTILS package

WEBDRIVER-CLIENT-UTILS

[PACKAGE]

Package with the purpose of reducing boilerplate.

The exported definitions work with an implicit element. The default implicit element is the current active element. So, it is not necessary to pass the element you are working with around most of the time.

External definitions

Variables

TIMEOUT

[WEBDRIVER-CLIENT-UTILS]

Default timeout value to use in selenium-utils functions.

DEFAULT-ELEMENT-FUNC

[WEBDRIVER-CLIENT-UTILS]

Function used to get the 'default element' by selenium-utils functions.

It is [ACTIVE-ELEMENT], page 16 function by default.

Functions

ID (&optional selector) [WEBDRIVER-CLIENT-UTILS]

Get active element id.

GET-COOKIE (cookie name) [WEBDRIVER-CLIENT-UTILS]

Get value of COOKIE at NAME.

Find element by SELECTOR. Returns NIL if the element is not found.

WAIT-FOR (selector & key (timeout *timeout*)) [WEBDRIVER-CLIENT-UTILS]

Wait for an element that matches SELECTOR to appear on the screen. TIMEOUT indicates how much time to wait (default is *TIMEOUT*).

CLASSNAME (&optional selector) [WEBDRIVER-CLIENT-UTILS]

Get active element classname.

TEXT (&optional selector) [WEBDRIVER-CLIENT-UTILS]

Get active element's text.

SEND-KEY (key &optional selector) [WEBDRIVER-CLIENT-UTILS]

Send a key to active element.

CLASSLIST (&optional selector) [WEBDRIVER-CLIENT-UTILS]

Get active element class list.

ATTR (name &optional selector) [WEBDRIVER-CLIENT-UTILS]

Get acttive element attribute.

SEND-KEYS (keys &optional selector) [WEBDRIVER-CLIENT-UTILS]

Send keys to active element.

ELEM (&optional selector) [WEBDRIVER-CLIENT-UTILS]

If SELECTOR is given, wait for an element that matches the selector to appear. Otherwise, call [*DEFAULT-ELEMENT-FUNC*], page 19 (the active element is re-

turned by default).

CLICK (&optional selector) [WEBDRIVER-CLIENT-UTILS]

Click on active element.

6 Index

 $({\rm Index}\ is\ nonexistent})$

*	\mathbf{W}
DEFAULT-CAPABILITIES	WEBDRIVER-CLIENT- UTILS:*DEFAULT-ELEMENT-FUNC*
\mathbf{A}	\mathbf{F}
ACCEPT-ALERT 14 ACTIVE-ELEMENT 16 ALERT-TEXT 14 ATTR 20	FIND-COOKIE 15 FIND-ELEM 20 FIND-ELEMENT 18 FIND-ELEMENTS 17 FIREFOX-CAPABILITIES 15
В	~
BACK	G GET-COOKIE
\mathbf{C}	ī
CHROME-CAPABILITIES 15 CLASSLIST 20 CLASSNAME 20	ID
CLICK 20 CLOSE-CURRENT-WINDOW 19 COOKIE 16	K KEY
D	L
DELETE-ALL-COOKIES 15 DELETE-COOKIE 15 DELETE-SESSION 13	LOG-TYPES 10 LOGS 10
DISMISS-ALERT	\mathbf{M}
E ELEM	MAKE-CAPABILITIES 11 MAKE-COOKIE 15 MAKE-SESSION 12 MERGE-CAPABILITIES 14 MOUSE-CLICK 10
ELEMENT-CLEAR 18 ELEMENT-CLICK 18 ELEMENT-DISPLAYED 17 ELEMENT-ENABLED 17	MOUSE-MOVE-TO
ELEMENT-ENABLED 17 ELEMENT-ID 10 ELEMENT-RECT 17 ELEMENT-SCREENSHOT 13 ELEMENT-SEND-KEYS 19 ELEMENT-TAGNAME 18	PAGE-SOURCE 11 PAGE-TITLE 11 PERFORM-ACTIONS 13
$\begin{array}{cccccccccccccccccccccccccccccccccccc$	R REFRESH

Chapter 6: Index 22

\mathbf{S}	WEBDRIVER-CLIENT: DISMISS-ALERT	14
SCREENSHOT	WEBDRIVER-CLIENT: ELEMENT-ATTRIBUTE 1	17
SEND-KEY	WEBDRIVER-CLIENT: ELEMENT-CLEAR 1	18
SEND-KEYS	WEBDRIVER-CLIENT: ELEMENT-CLICK 1	18
START-INTERACTIVE-SESSION	WEBDRIVER-CLIENT: ELEMENT-DISPLAYED 1	17
STOP-INTERACTIVE-SESSION	WEBDRIVER-CLIENT: ELEMENT-ENABLED	17
SWITCH-TO-FRAME	WEBDRIVER-CLIENT: ELEMENT-ID 1	10
5W11011 10 11WIND	WEBDRIVER-CLIENT: ELEMENT-RECT 1	17
TD.	WEBDRIVER-CLIENT: ELEMENT-SCREENSHOT 1	13
\mathbf{T}	WEBDRIVER-CLIENT: ELEMENT-SEND-KEYS 1	19
TEXT	WEBDRIVER-CLIENT: ELEMENT-TAGNAME	18
	WEBDRIVER-CLIENT: ELEMENT-TEXT	17
TT	WEBDRIVER-CLIENT: EXECUTE-SCRIPT	14
\mathbf{U}	WEBDRIVER-CLIENT:FIND-COOKIE 1	15
URL	WEBDRIVER-CLIENT:FIND-ELEMENT	18
USE-SESSION	WEBDRIVER-CLIENT:FIND-ELEMENTS	17
	WEBDRIVER-CLIENT: FIREFOX-CAPABILITIES 1	15
TT 7	WEBDRIVER-CLIENT: KEY 1	13
\mathbf{W}	WEBDRIVER-CLIENT:LOG-TYPES	10
WAIT-FOR	WEBDRIVER-CLIENT:LOGS 1	10
WEBDRIVER-CLIENT-UTILS:ATTR	WEBDRIVER-CLIENT: MAKE-CAPABILITIES 1	11
WEBDRIVER-CLIENT-UTILS:CLASSLIST	WEBDRIVER-CLIENT: MAKE-COOKIE 1	15
WEBDRIVER-CLIENT-UTILS:CLASSNAME	WEBDRIVER-CLIENT: MAKE-SESSION 1	
WEBDRIVER-CLIENT-UTILS:CLICK	WEBDRIVER-CLIENT: MERGE-CAPABILITIES 1	14
WEBDRIVER-CLIENT-UTILS:ELEM	WEBDRIVER-CLIENT: MOUSE-CLICK 1	10
WEBDRIVER-CLIENT-UTILS:FIND-ELEM	WEBDRIVER-CLIENT: MOUSE-MOVE-TO	10
WEBDRIVER-CLIENT-UTILS:GET-COOKIE 20	WEBDRIVER-CLIENT: PAGE-SOURCE 1	11
WEBDRIVER-CLIENT-UTILS:ID	WEBDRIVER-CLIENT: PAGE-TITLE 1	
WEBDRIVER-CLIENT-UTILS:SEND-KEY	WEBDRIVER-CLIENT: PERFORM-ACTIONS	13
WEBDRIVER-CLIENT-UTILS:SEND-KEYS	WEBDRIVER-CLIENT:REFRESH	11
WEBDRIVER-CLIENT-UTILS:TEXT	WEBDRIVER-CLIENT:SCREENSHOT 1	13
WEBDRIVER-CLIENT-UTILS:WAIT-FOR	WEBDRIVER-CLIENT:START-	
WEBDRIVER-CLIENT: ACCEPT-ALERT	INTERACTIVE-SESSION	12
WEBDRIVER-CLIENT:ACTIVE-ELEMENT	WEBDRIVER-CLIENT:STOP-	
WEBDRIVER-CLIENT: ALERT-TEXT 14	INTERACTIVE-SESSION	
WEBDRIVER-CLIENT:BACK	WEBDRIVER-CLIENT:SWITCH-TO-FRAME	
WEBDRIVER-CLIENT: CHROME-CAPABILITIES 15	WEBDRIVER-CLIENT:URL	
$\verb WEBDRIVER-CLIENT:CLOSE-CURRENT-WINDOW19 $	WEBDRIVER-CLIENT: USE-SESSION	
WEBDRIVER-CLIENT: COOKIE	WEBDRIVER-CLIENT:WEBDRIVER-STATUS 1	
${\tt WEBDRIVER-CLIENT:DELETE-ALL-COOKIES} \ \dots \ 15$	WEBDRIVER-CLIENT:WITH-SESSION	
$\verb WEBDRIVER-CLIENT:DELETE-COOKIE 15$	WEBDRIVER-STATUS	
WEBDRIVER-CLIENT: DELETE-SESSION	WITH-SESSION	12