Package 'padi'

April 6, 2006

Title PADI
Description Protocol for Application Database Interface
Depends R (>= 2.0.0), syskern (>= 2006.4-1), dsepadi, tframe (>= 2006.4-1)
Version 2006.4-1
LazyLoad yes
License Free. See the LICENCE file for details.
Author Paul Gilbert <pgilbert@bank-banque-canada.ca></pgilbert@bank-banque-canada.ca>
Maintainer Paul Gilbert <pgilbert@bank-banque-canada.ca></pgilbert@bank-banque-canada.ca>
URL http://www.bank-banque-canada.ca/pgilbert
R topics documented:
PADIserverProcess checkPADIserver getfm getpadi.default putpadi.default
Index
PADIserverProcess PADI Functions
Description
see details
Usage
<pre>PADIserverProcess() PADIcleanupScript() startPADIserver(server=Sys.info()[["nodename"]],</pre>

2 checkPADIserver

Arguments

server string or vector of strings indicating the server where the series will be found.

Scalar values are expanded to a vector of appropriate length.

dbname string or vector of strings indicating additional information for the server. Scalar

values are expanded to a vector of appropriate length.

server.process

string indicating the name of the process to be used to start a server process.

cleanup.script

string indicating the name of the process to be used to shut down a server pro-

cess.

process argument to cleanup.script, not actually the process ID.

kill.script string indicating the name of the process to be used to kill a server process.

Details

The function startPADIserver uses a script to start a server. The function cleanupPADIserver uses the information returned by startPADIserver to terminate the server. The function killPADIserver looks for a server and kills it. The default scripts for starting and stopping the server are determined by the functions PADIserverProcess and PADIcleanupScript, which use the Unix environment variables PADI, PADI_STARTUP and PADI_CLEANUP. Scripts for starting and stopping the server are only relevant in cases when it is necessary to start or stop a server.

Value

depends

See Also

getpadi putpadi

checkPADIserver

PADI Functions

Description

see details

Usage

Arguments

server string indicating the network name of the server."

user optional string indicating user ID used by the server to start the process."

timeout an integer indicating the number of seconds to wait before concluding that the

server is not available.

getfm 3

Details

The function load.padi loads the associated compiled C object code. The function checkPADIserver checks if a server is running.

Value

depends

See Also

```
getpadi putpadi getpadi.default putpadi.default
```

getfm

Function is for backwards compatability at the BOC

Description

Function is for backwards compatability at the BOC

Usage

```
getfm(dbname,series, starty=0,startp=0, endy=0,endp=0,
   nobs=0,max.obs=2000, transformations=NULL, pad=FALSE)
putfm(data, dbname, seriesNames)
```

Arguments

```
{\tt dbname}
```

series see getpadi.
starty see getpadi.
startp start period.
endy see getpadi.
endp end period.
nobs see getpadi.
max.obs see getpadi.

transformations

see getpadi.

pad see getpadi.

data a object with data to put on the server.
seriesNames vector of strings to use for series identifiers.

Details

Depreciated.

Value

```
see getpadi.
```

4 getpadi.default

See Also

```
getpadi.default getpadi
```

getpadi.default

Get Data from TSPADI Database Interface

Description

Get data from a TSPADI database interface.

Usage

Arguments

series A character string giving the name of the series. Alternately, series can be a

vector of character strings specifying multiple series.

server A character string giving the network name of the server which is to be requested

to supply the series. If series specifies multiple series and they are not all on the same server then server should be a vector of character strings with elements

corresponding to the elements of series.

dbname A character string giving additional information to the server about the location

of the series (eg. the name of a database). If series specifies multiple series and they are not all on the same database then dbname should be a vector of

character strings with elements corresponding to the elements of series.

starty An integer indicating the starting year.

startm An integer indicating the starting period.

startd An integer indicating the starting day.

endy An integer indicating the ending year.

endm An integer indicating the ending period.

endd An integer indicating the ending day.

nobs The number of observations.

max.obs integer indicating the possible returned data size used to define the size of the

buffer to prepare.

transformations

A character string giving transformations to be applied to the series (e.g. "log"). If multiple series are being requested then transformations can be a single string, in which case it is applied to all series, or a vector of character strings, one for each series. If no transformation is to be applied to some series then "" should be used.

getpadi.default 5

pad If FALSE (default) then all series are truncated to the interection of available

time periods (i.e. the latest start date and earliest end date). If TRUE then series are padded with NA so the result starts at the earliest available observation and

ends at the last available observation.

start.server try to start a server if one is not running server.process

command to execute in an attempt to start a server

cleanup.script

command to execute to terminate a server if one is started

user user id for access to the database (if necessary)
passwd password for access to the database (if necessary)

stop.on.error

If TRUE then stop is executed when an error occurs. Otherwise, the error mes-

sage is returned and the calling program must deal with it.

use.tframe If use.tframe=FALSE then ts() is used to construct the time series, otherwise the

tframe utilities are used. Certain transformations available with DSE require the tframe stucture and an error may result if these transformations are attempted

with use.tframe=FALSE.

warn Print warning messages for some crude frequency conversions (weekly data).

timeout an integer indicating the number of seconds to wait before concluding that the

server is not available.

Details

The function getpadi retrieves data from a (time series) server. The padi code is also available (including the PADI server side) at www.bank-banque-canada.ca/pgilbert.

(This documentation could use some cleaning up, but first I am really hoping to convert the whole interface to a more modern, non-RPC based, mechanism.)

start. and end dates or start dates and nobs can be supplied. If all are set to zero (the default) then all data is retrieved, provided max.obs is large enough. If more than one series is to be returned then series should be a vector of strings. In this case dbname must be a vector of corresponding length or a single string which is applied to all series. All series must have the same frequency. If the number of observations in any single series is larger than max.obs then an error will occur and max.obs should be set larger. For many data frequencies startd and endd can be omitted.

If start.server is FALSE then there will be no attempt to start a server and the function will stop if a server is not running. If start.server is TRUE (the default) then if server==Sys.info()[["nodename"]] (the default) and a server is not already running, there will be an attempt to start a server using the argument server.process. The default is determined by PADIserverProcess()

The argument server.process is only used if it is necessary to start a server.

If specified, server would typically be a single string, though there is some attempt to handle vectors of strings (indicating different servers for each series).

The string dbname is passed to the server, but it may or may not be used, depending on the server implementation. If the server is being started then it will run in the Unix pwd and local path names should work, BUT in general there is no guarantee that the server is running in the pwd and complete path names may be required.

Start and end dates or start dates and nobs can be supplied. If all are set to zero (the default) then all data is retrieved, provided max.obs is large enough.

6 getpadi.default

If the starting date and ending date and number of observations is set to zero, it will return the whole series. If the starting and ending dates are zero but number of observations is set, the LAST numbes observations are returned. If the starting date is sent, ending date is zero and numbes is non-zero, the FIRST numbes starting from start date are returned.

The size of the data array passed to C is the larger of nobs and max.obs. A ts matrix is returned. If more than one series is to be returned then series should be a vector of strings. In this case server must be a vector of corresponding length or a single string which is applied to all series. All series must have the same frequency and the time window is the intersection of the window for each series (i.e. the latest start and earliest end date). startd and endd provide for a tag (day).

If the starting date and ending date and number of observations is set to zero, it will return the whole series. If the starting and ending dates are zero but number of observations is set, the LAST numbes observations are returned. If the starting date is sent, ending date is zero and numbes is non-zero, the FIRST numbes starting from start date are returned.

If transformations is not null it should be a vector of strings, one for each series (with "" for any series which is not to be transformed), or a single string which is applied to each series. The transformations are applied by eval(call(transformations[i], .).

If use.tframe=FALSE then ts() is used to construct the time series, otherwise the tframe approach is used. (See the tframe package.) Certain transformations available with DSE require the tframe structure and an error may result if these transformations are attempted with use.tframe=FALSE.

If stop.on.error is TRUE then stop is executed if a data retrieval error occurs. If stop.on.error is FALSE then the error message is returned, which means the calling function will need to handle the error.

If warn is TRUE then warnings are issued for certain data conversions (weekly data) which may not work in all case. If warn is these warnings are not issued. timeout is the period to wait (in seconds) before generating an error.

Value

A time series matrix with a column for each series.

See Also

checkPADIserver putpadi.default getpadi putpadi

Examples

```
if(require("padi") && checkPADIserver("ets")){
   cpi <-getpadi("P100000", server= "ets")# June 1992=100
   cpi <-getpadi("P100000", starty=1988, startm=1,endy=1990, endm=12, server= "ets")
   cpi <-getpadi( "P100000", starty=1988, startm=1,nobs=8, server= "ets")
   data <- getpadi( c("V122491","V37124","P100000"), server= "ets")

cpi <-getpadi("P100000", server= "ets", use.tframe=TRUE)
   data <- getpadi( c("V122491","V37124","P100000"), server= "ets", use.tframe=TRUE)
}</pre>
```

putpadi.default 7

putpadi.default PADI Functions

Description

see details

Usage

Arguments

data a tfPADIdata object with data to put on the server.

server string or vector of strings indicating the server where the series will be found.

Scalar values are expanded to a vector of appropriate length.

dbname string or vector of strings indicating additional information for the server. Scalar

values are expanded to a vector of appropriate length.

series vector of strings to use for series identifiers.

start.server logical indicating if a (local) server should be started.

server.process

string indicating the name to be used to start a server process.

cleanup.script

string indicating the name to be used to shut down a server process.

user an optional string used by the server to check permission.

passwd an optional string used by the server to check permission.

stop.on.error

logical indicating if the function should stop if any series produces an error, or

continue with other series.

warn logical indicating if warning messages should be supressed.

timeout an integer indicating the number of seconds to wait before concluding that the

server is not available.

Details

The function putpadi writes data to a specified databases on a specified server (default local).

If start.server is FALSE then there will be no attempt to start a server and the function will stop if a server is not running. If start.server is TRUE (the default) then if server==Sys.info()[["nodename"]] (the default) and a server is not already running, there will be an attempt to start a server using the argument server.process. The default is a "local mode" Fame server.

The argument server process is only used if it is necessary to start a server.

8 putpadi.default

If specified, server would typically be a single string, though there is some attempt to handle vectors of strings (indicating different servers for each series).

dbname should typically be supplied. (but some servers might accept an empty string ("") or ignore any string supplied. If the server is being started then it will run in the Unix pwd and local path names should work, BUT in general there is no guarantee that the server is running in the pwd and complete path names may be required. data can be a vector, matrix, time series or time series matrix. Dates are used when available. If data is a vector or single time series, then server, dbname, and series should have length 1. If data is a matrix or time series matrix with more than one series then server, dbname, and series should be character strings of the same length or, server and dbname can be length 1, in which case the string will be repeated for all series. If they do not exist then an error is indicated. The strings user and passwd are passed to the server, but may or may not be used, depending on the server implementation. If stop.on.error is TRUE (default) the function stops if there is an error writing any series. Otherwise, the result is TRUE or FALSE for each series, indicating success or failure.

Value

depends

See Also

checkPADIserver putpadi getpadi getpadi.default putpadi.default

Index

```
*Topic ts
    checkPADIserver, 2
    getfm, 3
    getpadi.default,4
   PADIserverProcess, 1
   putpadi.default,7
checkPADIserver, 2, 6, 8
cleanupPADIserver
       (PADIserverProcess), 1
{\tt getfm}, {\tt 3}
getpadi, 2-4, 6, 8
getpadi.default, 3, 4, 4, 8
killPADIserver
       (PADIserverProcess), 1
PADIcleanupScript
       (PADIserverProcess), 1
PADIserverProcess, 1
putfm (getfm), 3
putpadi, 2, 3, 6, 8
putpadi.default, 3, 6, 7, 8
startPADIserver
       (PADIserverProcess), 1
```