Managing Space for Schema Objects

Managing space for schema objects involves tasks such as managing tablespace alerts and space allocation, reclaiming unused space, dropping unused object storage, monitoring space usage, and capacity planning.

Managing Tablespace Alerts

Oracle Database provides proactive help in managing disk space for tablespaces by alerting you when available space is running low.

Managing Resumable Space Allocation

You can suspend, and later resume, the execution of large database operations.

Reclaiming Unused Space

You can reclaim unused space. Segment Advisor, is an Oracle Database component that identifies segments that have space available for reclamation.

Dropping Unused Object Storage

The <code>DBMS_SPACE_ADMIN</code> package includes the <code>DROP_EMPTY_SEGMENTS</code> procedure, which enables you to drop segments for empty tables and partitions that have been migrated from previous releases. This includes segments of dependent objects of the table, such as index segments, where possible.

Understanding Space Usage of Data Types

When creating tables and other data structures, you must know how much space they will require. Each data type has different space requirements.

Displaying Information About Space Usage for Schema Objects

Oracle Database provides data dictionary views and PL/SQL packages that allow you to display information about the space usage of schema objects.

Capacity Planning for Database Objects

Oracle Database provides two ways to plan capacity for database objects: with Cloud Control or with the <code>DBMS_SPACE</code> PL/SQL package. Three procedures in the <code>DBMS_SPACE</code> package enable you to predict the size of new objects and monitor the size of existing database objects.

18.1 Managing Tablespace Alerts

Oracle Database provides proactive help in managing disk space for tablespaces by alerting you when available space is running low.

About Managing Tablespace Alerts

Two alert thresholds are defined by default: **warning** and **critical**. The warning threshold is the limit at which space is beginning to run low. The critical threshold is a serious limit that warrants your immediate attention. The database issues alerts at both thresholds.

Setting Alert Thresholds

For each tablespace, you can set just percent-full thresholds, just free-space-remaining thresholds, or both types of thresholds simultaneously. Setting either type of threshold to zero disables it.

Viewing Alerts

You view alerts by accessing a Database Home page in Cloud Control and viewing the Incidents and Problems section.

Limitations

Threshold-based alerts have the some limitations.

18.1.1 About Managing Tablespace Alerts

Two alert thresholds are defined by default: **warning** and **critical**. The warning threshold is the limit at which space is beginning to run low. The critical threshold is a serious limit that warrants your immediate attention. The database issues alerts at both thresholds.

There are two ways to specify alert thresholds for both locally managed and dictionary managed tablespaces:

By percent full

For both warning and critical thresholds, when space used becomes greater than or equal to a percent of total space, an alert is issued.

By free space remaining (in kilobytes (KB))

For both warning and critical thresholds, when remaining space falls below an amount in KB, an alert is issued. Free-space-remaining thresholds are more useful for very large tablespaces.

Alerts for locally managed tablespaces are server-generated. For dictionary managed tablespaces, Oracle Enterprise Manager Cloud Control (Cloud Control) provides this functionality. See "Monitoring a Database with Server-Generated Alerts" for more information.

New tablespaces are assigned alert thresholds as follows:

- Locally managed tablespace—When you create a new locally managed tablespace, it is
 assigned the default threshold values defined for the database. A newly created database
 has a default of 85% full for the warning threshold and 97% full for the critical threshold.
 Defaults for free space remaining thresholds for a new database are both zero (disabled).
 You can change these database defaults, as described later in this section.
- Dictionary managed tablespace—When you create a new dictionary managed tablespace, it is assigned the threshold values that Cloud Control lists for "All others" in the metrics categories "Tablespace Free Space (MB) (dictionary managed)" and "Tablespace Space Used (%) (dictionary managed)." You change these values on the Metric and Policy Settings page.

Note:

In a database that is upgraded from Oracle 9*i* or earlier to Oracle Database 10*g* or later, database defaults for all locally managed tablespace alert thresholds are set to zero. This setting effectively disables the alert mechanism to avoid excessive alerts in a newly migrated database.



18.1.2 Setting Alert Thresholds

For each tablespace, you can set just percent-full thresholds, just free-space-remaining thresholds, or both types of thresholds simultaneously. Setting either type of threshold to zero disables it.

The ideal setting for the warning threshold is one that issues an alert early enough for you to resolve the problem before it becomes critical. The critical threshold should be one that issues an alert still early enough so that you can take immediate action to avoid loss of service.

To set alert threshold values for locally managed tablespaces:

- Do one of the following:
 - Use the Tablespaces page of Cloud Control.
 - See the Cloud Control online help for information about changing the space usage alert thresholds for a tablespace.
 - Use the DBMS_SERVER_ALERT.SET_THRESHOLD package procedure.
 See Oracle Database PL/SQL Packages and Types Reference for details.

To set alert threshold values for dictionary managed tablespaces:

Use the Tablespaces page of Cloud Control.

See the Cloud Control online help for information about changing the space usage alert thresholds for a tablespace.

Example - Setting an Alert Threshold with Cloud Control

You receive an alert in Cloud Control when a space usage threshold for a tablespace is reached. There are two types of space usage alerts that you can enable: **warning**, for when tablespace is somewhat low, and **critical**, for when the tablespace is almost completely full and action must be taken immediately.

For both warning and critical alerts, you can specify alert thresholds in the following ways:

By space used (%)

When space used becomes greater than or equal to a percentage of total space, an alert is issued.

By free space (MB)

When remaining space falls below an amount (in MB), an alert is issued.

Free-space thresholds are more useful for large tablespaces. For example, for a 10 TB tablespace, setting the percentage full critical alert to as high as 99 percent means that the database would issue an alert when there is still 100 GB of free space remaining. Usually, 100 GB remaining would not be a critical situation, and the alert would not be useful. For this tablespace, it might be better to use a free-space threshold, which you could set to issue a critical alert when 5 GB of free space remains.

For both warning and critical alerts for a tablespace, you can enable either the space used threshold or the free-space threshold, or you can enable both thresholds.

To change space usage alert thresholds for tablespaces:

1. Go to the Database Home page.



From the Administration menu, select Storage, then Tablespaces.

The Tablespaces page appears.

Select the tablespace whose threshold you want to change, and then click Edit.

The Edit Tablespace page appears, showing the General subpage.

- 4. Click the **Thresholds** tab at the top of the page to display the Thresholds subpage.
- 5. In the Space Used (%) section, do one of the following:
 - Accept the default thresholds.
 - Select Specify Thresholds, and then enter a Warning (%) threshold and a Critical (%) threshold.
 - Select Disable Thresholds to disable the percentage full thresholds.
- 6. In the Free Space (MB) section, do one of the following:
 - Accept the default thresholds.
 - Select Specify Thresholds, and then enter a Warning (MB) threshold and a Critical (MB) threshold.
 - Select Disable Thresholds to disable the threshold for free space remaining.
- 7. Click Apply.

A confirmation message appears.

Example—Setting an Alert Threshold Value with a Package Procedure

The following example sets the free-space-remaining thresholds in the USERS tablespace to 10 MB (warning) and 2 MB (critical), and disables the percent-full thresholds. The USERS tablespace is a locally managed tablespace.





When setting nonzero values for percent-full thresholds, use the greater-than-or-equal-to operator, OPERATOR GE.

Restoring a Tablespace to Database Default Thresholds


After explicitly setting values for locally managed tablespace alert thresholds, you can cause the values to revert to the database defaults by setting them to <code>NULL</code> with <code>DBMS SERVER ALERT.SET THRESHOLD</code>.

Modifying Database Default Thresholds

To modify database default thresholds for locally managed tablespaces, invoke DBMS_SERVER_ALERT.SET_THRESHOLD as shown in the previous example, but set <code>object_name</code> to <code>NULL</code>. All tablespaces that use the database default are then switched to the new default.

18.1.3 Viewing Alerts

You view alerts by accessing a Database Home page in Cloud Control and viewing the Incidents and Problems section.



You can also view alerts for locally managed tablespaces with the DBA_OUTSTANDING_ALERTS view. See "Server-Generated Alerts Data Dictionary Views" for more information.

18.1.4 Limitations

Threshold-based alerts have the some limitations.

These limitations include the following:

- Alerts are not issued for locally managed tablespaces that are offline or in read-only mode.
 However, the database reactivates the alert system for such tablespaces after they become read/write or available.
- When you take a tablespace offline or put it in read-only mode, you should disable the alerts for the tablespace by setting the thresholds to zero. You can then reenable the alerts

by resetting the thresholds when the tablespace is once again online and in read/write mode.

See Also:

- "Monitoring a Database with Server-Generated Alerts" for additional information on server-generated alerts in general
- Oracle Database PL/SQL Packages and Types Reference for information on the procedures of the DBMS SERVER ALERT package and how to use them
- "Reclaiming Unused Space" for various ways to reclaim space that is no longer being used in the tablespace
- "Purging Objects in the Recycle Bin" for information on reclaiming recycle bin space

18.2 Managing Resumable Space Allocation

You can suspend, and later resume, the execution of large database operations.

- Resumable Space Allocation Overview
 - Oracle Database provides a means for suspending, and later resuming, the execution of large database operations in the event of space allocation failures. Therefore, you can take corrective action instead of the Oracle Database server returning an error to the user. After the error condition is corrected, the suspended operation automatically resumes. This feature is called **resumable space allocation**. The statements that are affected are called resumable statements.
- Enabling and Disabling Resumable Space Allocation
 You enable and disable resumable space allocation by running SQL statements and setting certain initialization parameters.
- Using a LOGON Trigger to Set Default Resumable Mode
 Another method of setting default resumable mode, other than setting the
 RESUMABLE_TIMEOUT initialization parameter, is that you can register a database level LOGON trigger to alter a user's session to enable resumable and set a timeout interval.
- Detecting Suspended Statements
 - When a resumable statement is suspended, the error is not raised to the client. In order for corrective action to be taken, Oracle Database provides alternative methods for notifying users of the error and for providing information about the circumstances.
- Operation-Suspended Alert
 When a resumable session is suspended, an operation-suspended alert is issued on the object that needs allocation of resource for the operation to complete.
- Resumable Space Allocation Example: Registering an AFTER SUSPEND Trigger
 An example illustrates how to create a system wide AFTER SUSPEND trigger and register it
 as user SYS at the database level.

18.2.1 Resumable Space Allocation Overview

Oracle Database provides a means for suspending, and later resuming, the execution of large database operations in the event of space allocation failures. Therefore, you can take

corrective action instead of the Oracle Database server returning an error to the user. After the error condition is corrected, the suspended operation automatically resumes. This feature is called **resumable space allocation**. The statements that are affected are called resumable statements.

- How Resumable Space Allocation Works
 An overview shows how resumable space allocation works.
- What Operations are Resumable?
 Some operations are resumable.
- What Errors are Correctable?
 Some errors are correctable.
- Resumable Space Allocation and Distributed Operations
 In a distributed environment, if a user enables or disables resumable space allocation, or a DBA alters the RESUMABLE_TIMEOUT initialization parameter, then the local instance is affected. RESUMABLE cannot be enabled remotely.
- Parallel Execution and Resumable Space Allocation
 In parallel execution, if one of the parallel execution server processes encounters a correctable error, then that server process suspends its execution.

18.2.1.1 How Resumable Space Allocation Works

An overview shows how resumable space allocation works.

- 1. A statement executes in resumable mode only if its session has been enabled for resumable space allocation by one of the following actions:
 - The ALTER SESSION ENABLE RESUMABLE statement is issued in the session before the statement executes when the RESUMABLE_TIMEOUT initialization parameter is set to a nonzero value.
 - The ALTER SESSION ENABLE RESUMABLE TIMEOUT timeout_value statement is issued
 in the session before the statement executes, and the timeout_value is a nonzero
 value.
- 2. A resumable statement is suspended when one of the following conditions occur (these conditions result in corresponding errors being signalled for non-resumable statements):
 - Out of space condition
 - Maximum extents reached condition
 - Space guota exceeded condition.
- 3. When the execution of a resumable statement is suspended, there are mechanisms to perform user supplied operations, log errors, and query the status of the statement execution. When a resumable statement is suspended the following actions are taken:
 - The error is reported in the alert log.
 - The system issues the Resumable Session Suspended alert.
 - If the user registered a trigger on the AFTER SUSPEND system event, the user trigger is executed. A user supplied PL/SQL procedure can access the error message data using the DBMS RESUMABLE package and the DBA or USER RESUMABLE view.
- Suspending a statement automatically results in suspending the transaction. Thus all transactional resources are held through a statement suspend and resume.



- 5. When the error condition is resolved (for example, as a result of user intervention or perhaps sort space released by other queries), the suspended statement automatically resumes execution and the Resumable Session Suspended alert is cleared.
- 6. A suspended statement can be forced to throw the exception using the DBMS_RESUMABLE.ABORT() procedure. This procedure can be called by a DBA, or by the user who issued the statement.
- 7. A suspension time out interval, specified by the RESUMABLE_TIMEOUT initialization parameter or by the timeout value in the ALTER SESSION ENABLE RESUMABLE TIMEOUT statement, is associated with resumable statements. A resumable statement that is suspended for the timeout interval wakes up and returns the exception to the user if the error condition is not resolved within the timeout interval.
- 8. A resumable statement can be suspended and resumed multiple times during execution.

18.2.1.2 What Operations are Resumable?

Some operations are resumable.

The following operations are resumable:

Queries

SELECT statements that run out of temporary space (for sort areas) are candidates for resumable execution. When using OCI, the calls <code>OCIStmtExecute()</code> and <code>OCIStmtFetch()</code> are candidates.

DML

INSERT, UPDATE, and DELETE statements are candidates. The interface used to execute them does not matter; it can be OCI, PL/SQL, or another interface. Also, INSERT INTO...SELECT from external tables can be resumable.

Import/Export

As for SQL*Loader, a command line parameter controls whether statements are resumable after recoverable errors.

DDL

The following statements are candidates for resumable execution:

- CREATE TABLE ... AS SELECT
- CREATE INDEX
- ALTER INDEX ... REBUILD
- ALTER TABLE ... MOVE PARTITION
- ALTER TABLE ... SPLIT PARTITION
- ALTER INDEX ... REBUILD PARTITION
- ALTER INDEX ... SPLIT PARTITION
- CREATE MATERIALIZED VIEW
- CREATE MATERIALIZED VIEW LOG

18.2.1.3 What Errors are Correctable?

Some errors are correctable.



There are three classes of correctable errors:

Out of space condition

The operation cannot acquire any more extents for a table/index/temporary segment/undo segment/cluster/LOB/table partition/index partition in a tablespace. For example, the following errors fall in this category:

```
ORA-01653 unable to extend table \dots in tablespace \dots ORA-01654 unable to extend index \dots in tablespace \dots
```

Maximum extents reached condition

The number of extents in a table/index/temporary segment/undo segment/cluster/LOB/ table partition/index partition equals the maximum extents defined on the object. For example, the following errors fall in this category:

```
ORA-01631 max # extents ... reached in table ... ORA-01632 max # extents ... reached in index ...
```

Space quota exceeded condition

The user has exceeded their assigned space quota in the tablespace. Specifically, this is noted by the following error:

```
ORA-01536 space quote exceeded for tablespace string
```

18.2.1.4 Resumable Space Allocation and Distributed Operations

In a distributed environment, if a user enables or disables resumable space allocation, or a DBA alters the RESUMABLE_TIMEOUT initialization parameter, then the local instance is affected. RESUMABLE cannot be enabled remotely.

In a distributed transaction, sessions on remote instances are suspended only if the remote instance has already enabled RESUMABLE on the instance or sessions at its site.

18.2.1.5 Parallel Execution and Resumable Space Allocation

In parallel execution, if one of the parallel execution server processes encounters a correctable error, then that server process suspends its execution.

Other parallel execution server processes will continue executing their respective tasks, until either they encounter an error or are blocked (directly or indirectly) by the suspended server process. When the correctable error is resolved, the suspended process resumes execution and the parallel operation continues execution. If the suspended operation is terminated, then the parallel operation terminates, throwing the error to the user.

Different parallel execution server processes may encounter one or more correctable errors. This may result in firing an AFTER SUSPEND trigger multiple times, in parallel. Also, if a parallel execution server process encounters a non-correctable error while another parallel execution server process is suspended, the suspended statement is immediately terminated.

For parallel execution, every parallel execution coordinator and server process has its own entry in the DBA_ or USER RESUMABLE view.

18.2.2 Enabling and Disabling Resumable Space Allocation

You enable and disable resumable space allocation by running SQL statements and setting certain initialization parameters.

- About Enabling and Disabling Resumable Space Allocation
 Resumable space allocation is only possible when statements are executed within a
 session that has resumable mode enabled.
- Setting the RESUMABLE_TIMEOUT Initialization Parameter
 You can specify a default system wide timeout interval by setting the RESUMABLE_TIMEOUT initialization parameter.
- Using ALTER SESSION to Enable and Disable Resumable Space Allocation
 Within a session, a user can issue the ALTER SESSION SET statement to set the
 RESUMABLE_TIMEOUT initialization parameter and enable resumable space allocation,
 change a timeout value, or to disable resumable mode.

18.2.2.1 About Enabling and Disabling Resumable Space Allocation

Resumable space allocation is only possible when statements are executed within a session that has resumable mode enabled.

Resumable space allocation is enabled for a session when the ALTER SESSION ENABLE RESUMABLE statement is executed, and the RESUMABLE_TIMEOUT initialization parameter is set to a non-zero value for the session. When the RESUMABLE_TIMEOUT initialization parameter is set at the system level, it is the default for an ALTER SESSION ENABLE RESUMABLE statement that does not specify a timeout value. When an ALTER SESSION ENABLE RESUMABLE statement specifies a timeout value, it overrides the system default.

Resumable space allocation is disabled for a session in all of the following cases when the ALTER SESSION ENABLE RESUMABLE statement is executed:

- The session does not execute an ALTER SESSION ENABLE RESUMABLE statement.
- The session executes an ALTER SESSION DISABLE RESUMABLE statement.
- The session executes an ALTER SESSION ENABLE RESUMABLE statement, and the timeout value is zero.

Note:

Because suspended statements can hold up some system resources, users must be granted the RESUMABLE system privilege before they are allowed to enable resumable space allocation and execute resumable statements.

18.2.2.2 Setting the RESUMABLE_TIMEOUT Initialization Parameter

You can specify a default system wide timeout interval by setting the RESUMABLE_TIMEOUT initialization parameter.

For example, the following setting of the RESUMABLE_TIMEOUT parameter in the initialization parameter file sets the timeout period to 1 hour:

```
RESUMABLE TIMEOUT = 3600
```

If this parameter is set to 0, then resumable space allocation is disabled even for sessions that run an Alter session enable resumable statement without a timeout value.

You can also use the ALTER SYSTEM SET statement to change the value of this parameter at the system level. For example, the following statement disables resumable space allocation for all sessions that run an ALTER SESSION ENABLE RESUMABLE statement without a timeout value:

ALTER SYSTEM SET RESUMABLE TIMEOUT=0;

18.2.2.3 Using ALTER SESSION to Enable and Disable Resumable Space Allocation

Within a session, a user can issue the ALTER SESSION SET statement to set the RESUMABLE_TIMEOUT initialization parameter and enable resumable space allocation, change a timeout value, or to disable resumable mode.

A user can enable resumable mode for a session with the default system RESUMABLE_TIMEOUT value using the following SQL statement:

ALTER SESSION ENABLE RESUMABLE;

To disable resumable mode, a user issues the following statement:

ALTER SESSION DISABLE RESUMABLE;

The default for a new session is resumable mode disabled.

The user can also specify a timeout interval, and can provide a name used to identify a resumable statement. These are discussed separately in following sections.

Specifying a Timeout Interval

When you enable resumable mode, you can set a timeout period, after which a suspended statement will error if no intervention has taken place.

Naming Resumable Statements

Possumable statements can be identified.

Resumable statements can be identified by name.



"Using a LOGON Trigger to Set Default Resumable Mode"

18.2.2.3.1 Specifying a Timeout Interval

When you enable resumable mode, you can set a timeout period, after which a suspended statement will error if no intervention has taken place.

The following statement specifies that resumable transactions will time out and error after 3600 seconds:

ALTER SESSION ENABLE RESUMABLE TIMEOUT 3600;

The value of TIMEOUT remains in effect until it is changed by another ALTER SESSION ENABLE RESUMABLE statement, it is changed by another means, or the session ends. If the RESUMABLE_TIMEOUT initialization parameter is not set, then the default timeout interval when using the ENABLE RESUMABLE TIMEOUT clause to enable resumable mode is 7200 seconds.



See Also:

"Setting the RESUMABLE_TIMEOUT Initialization Parameter" for other methods of changing the timeout interval for resumable space allocation

18.2.2.3.2 Naming Resumable Statements

Resumable statements can be identified by name.

The following statement assigns a name to resumable statements:

ALTER SESSION ENABLE RESUMABLE TIMEOUT 3600 NAME 'insert into table';

The NAME value remains in effect until it is changed by another ALTER SESSION ENABLE RESUMABLE statement, or the session ends. The default value for NAME is 'User username(userid), Session sessionid, Instance instanceid'.

The name of the statement is used to identify the resumable statement in the DBA_RESUMABLE and USER RESUMABLE views.

18.2.3 Using a LOGON Trigger to Set Default Resumable Mode

Another method of setting default resumable mode, other than setting the RESUMABLE_TIMEOUT initialization parameter, is that you can register a database level LOGON trigger to alter a user's session to enable resumable and set a timeout interval.

Note:

If there are multiple triggers registered that change default mode and timeout for resumable statements, the result will be unspecified because Oracle Database does not guarantee the order of trigger invocation.

18.2.4 Detecting Suspended Statements

When a resumable statement is suspended, the error is not raised to the client. In order for corrective action to be taken, Oracle Database provides alternative methods for notifying users of the error and for providing information about the circumstances.

- Notifying Users: The AFTER SUSPEND System Event and Trigger
 When a resumable statement encounters a correctable error, the system internally
 generates the AFTER SUSPEND system event. Users can register triggers for this event at
 both the database and schema level. If a user registers a trigger to handle this system
 event, the trigger is executed after a SQL statement has been suspended.
- Using Views to Obtain Information About Suspended Statements
 You can guery a set of views for information about the status of resumable statements.
- Using the DBMS_RESUMABLE Package
 The DBMS RESUMABLE package helps control resumable space allocation.

18.2.4.1 Notifying Users: The AFTER SUSPEND System Event and Trigger

When a resumable statement encounters a correctable error, the system internally generates the AFTER SUSPEND system event. Users can register triggers for this event at both the database and schema level. If a user registers a trigger to handle this system event, the trigger is executed after a SQL statement has been suspended.

SQL statements executed within a AFTER SUSPEND trigger are always non-resumable and are always autonomous. Transactions started within the trigger use the SYSTEM rollback segment. These conditions are imposed to overcome deadlocks and reduce the chance of the trigger experiencing the same error condition as the statement.

Users can use the <code>USER_RESUMABLE</code> or <code>DBA_RESUMABLE</code> views, or the <code>DBMS_RESUMABLE.SPACE_ERROR_INFO</code> function, within triggers to get information about the resumable statements.

Triggers can also call the <code>DBMS_RESUMABLE</code> package to terminate suspended statements and modify resumable timeout values. In the following example, the default system timeout is changed by creating a system wide <code>AFTER SUSPEND</code> trigger that calls <code>DBMS_RESUMABLE</code> to set the timeout to 3 hours:

```
CREATE OR REPLACE TRIGGER resumable_default_timeout
AFTER SUSPEND
ON DATABASE
BEGIN
DBMS_RESUMABLE.SET_TIMEOUT(10800);
END;
/
```

See Also:

Oracle Database PL/SQL Language Reference for information about triggers and system events

18.2.4.2 Using Views to Obtain Information About Suspended Statements

You can guery a set of views for information about the status of resumable statements.

View	Description
DBA_RESUMABLE	These views contain rows for all currently executing or suspended
USER_RESUMABLE	resumable statements. They can be used by a DBA, AFTER SUSPEND trigger, or another session to monitor the progress of, or obtain specific information about, resumable statements.
V\$SESSION_WAIT	When a statement is suspended the session invoking the statement is put into a wait state. A row is inserted into this view for the session with the EVENT column containing "statement suspended, wait error to be cleared".



18.2.4.3 Using the DBMS RESUMABLE Package

The DBMS RESUMABLE package helps control resumable space allocation.

You can invoke the following procedures:

Procedure	Description
ABORT (sessionID)	This procedure terminates a suspended resumable statement. The parameter sessionID is the session ID in which the statement is executing. For parallel DML/DDL, sessionID is any session ID which participates in the parallel DML/DDL.
	Oracle Database guarantees that the ABORT operation always succeeds. It may be called either inside or outside of the AFTER SUSPEND trigger.
	The caller of ABORT must be the owner of the session with sessionID, have ALTER SYSTEM privilege, or have DBA privileges.
<pre>GET_SESSION_TIMEOUT(sessionID)</pre>	This function returns the current timeout value of resumable space allocation for the session with sessionID. This returned timeout is in seconds. If the session does not exist, this function returns -1.
<pre>SET_SESSION_TIMEOUT(sessionID, timeout)</pre>	This procedure sets the timeout interval of resumable space allocation for the session with <code>sessionID</code> . The parameter <code>timeout</code> is in seconds. The new <code>timeout</code> setting will applies to the session immediately. If the session does not exist, no action is taken.
GET_TIMEOUT()	This function returns the current timeout value of resumable space allocation for the current session. The returned value is in seconds.
SET_TIMEOUT(timeout)	This procedure sets a timeout value for resumable space allocation for the current session. The parameter timeout is in seconds. The new timeout setting applies to the session immediately.



Oracle Database PL/SQL Packages and Types Reference for details about the DBMS RESUMABLE package.

18.2.5 Operation-Suspended Alert

When a resumable session is suspended, an operation-suspended alert is issued on the object that needs allocation of resource for the operation to complete.

Once the resource is allocated and the operation completes, the operation-suspended alert is cleared. See "Managing Tablespace Alerts" for more information on system-generated alerts.

18.2.6 Resumable Space Allocation Example: Registering an AFTER SUSPEND Trigger

An example illustrates how to create a system wide AFTER SUSPEND trigger and register it as user SYS at the database level.

Whenever a resumable statement is suspended in any session, this trigger can have either of two effects:

- If an undo segment has reached its space limit, then a message is sent to the DBA and the statement is terminated.
- If any other recoverable error has occurred, the timeout interval is reset to 8 hours.

Here are the statements for this example:

```
CREATE OR REPLACE TRIGGER resumable default
AFTER SUSPEND
ON DATABASE
DECLARE
   /* declare transaction in this trigger is autonomous */
   /* this is not required because transactions within a trigger
      are always autonomous */
   PRAGMA AUTONOMOUS TRANSACTION;
  cur_sid NUMBER;
cur_inst NUMBER;
errno NUMBER;
err_type VARCHAR2;
object_owner VARCHAR2;
object_type VARCHAR2;
   table space name VARCHAR2;
   object name VARCHAR2;
   sub_object_name VARCHAR2;
  error_txt VARCHAR2;
msg_body VARCHAR2;
ret_value BOOLEAN;
mail_conn UTL_SMTP.CONNECTION;
BEGIN
   -- Get session ID
   SELECT DISTINCT(SID) INTO cur SID FROM V$MYSTAT;
   -- Get instance number
   cur inst := userenv('instance');
   -- Get space error information
   ret value :=
   DBMS RESUMABLE.SPACE_ERROR_INFO(err_type,object_type,object_owner,
         table space name, object name, sub object name);
   -- If the error is related to undo segments, log error, send email
   -- to DBA, and terminate the statement. Otherwise, set timeout to 8 hours.
   -- sys.rbs error is a table which is to be
   -- created by a DBA manually and defined as
   -- (sql text VARCHAR2(1000), error msg VARCHAR2(4000),
   -- suspend time DATE)
   IF OBJECT TYPE = 'UNDO SEGMENT' THEN
       /* LOG ERROR */
```

```
INSERT INTO sys.rbs error (
          SELECT SQL TEXT, ERROR MSG, SUSPEND TIME
          FROM DBMS RESUMABLE
          WHERE SESSION ID = cur sid AND INSTANCE ID = cur inst
       SELECT ERROR MSG INTO error txt FROM DBMS RESUMABLE
          WHERE SESSION ID = cur sid and INSTANCE ID = cur inst;
        -- Send email to receipient through UTL SMTP package
       msg body:='Subject: Space Error Occurred
                   Space limit reached for undo segment ' || object name ||
                   on ' || TO_CHAR(SYSDATE, 'Month dd, YYYY, HH:MIam') ||
                   '. Error message was ' || error txt;
       mail conn := UTL SMTP.OPEN CONNECTION('localhost', 25);
       UTL SMTP.HELO(mail conn, 'localhost');
       UTL SMTP.MAIL(mail conn, 'sender@localhost');
       UTL SMTP.RCPT(mail conn, 'recipient@localhost');
       UTL SMTP.DATA(mail conn, msg_body);
       UTL SMTP.QUIT (mail conn);
        -- Terminate the statement
       DBMS RESUMABLE.ABORT (cur sid);
    ELSE
        -- Set timeout to 8 hours
       DBMS RESUMABLE.SET TIMEOUT(28800);
    /* commit autonomous transaction */
END;
```

18.3 Reclaiming Unused Space

You can reclaim unused space. Segment Advisor, is an Oracle Database component that identifies segments that have space available for reclamation.

About Reclaimable Unused Space

Over time, updates and deletes on objects within a tablespace can create pockets of empty space that individually are not large enough to be reused for new data. This type of empty space is referred to as fragmented free space.

The Segment Advisor

The Segment Advisor identifies segments that have space available for reclamation.

Shrinking Database Segments Online

You use online segment shrink to reclaim fragmented free space below the high water mark in an Oracle Database segment.

Deallocating Unused Space

When you deallocate unused space, the database frees the unused space at the unused (high water mark) end of the database segment and makes the space available for other segments in the tablespace.

18.3.1 About Reclaimable Unused Space

Over time, updates and deletes on objects within a tablespace can create pockets of empty space that individually are not large enough to be reused for new data. This type of empty space is referred to as fragmented free space.

Objects with fragmented free space can result in much wasted space, and can impact database performance. The preferred way to defragment and reclaim this space is to perform an **online segment shrink**. This process consolidates fragmented free space below the high water mark and compacts the segment. After compaction, the high water mark is moved, resulting in new free space above the high water mark. That space above the high water mark is then deallocated. The segment remains available for queries and DML during most of the operation, and no extra disk space need be allocated.

You use the **Segment Advisor** to identify segments that would benefit from online segment shrink. Only segments in locally managed tablespaces with automatic segment space management (ASSM) are eligible. Other restrictions on segment type exist. For more information, see "Shrinking Database Segments Online".

If a table with reclaimable space is not eligible for online segment shrink, or if you want to make changes to logical or physical attributes of the table while reclaiming space, then you can use **online table redefinition** as an alternative to segment shrink. Online redefinition is also referred to as **reorganization**. Unlike online segment shrink, it requires extra disk space to be allocated. See "Redefining Tables Online" for more information.

18.3.2 The Segment Advisor

The Segment Advisor identifies segments that have space available for reclamation.

- About the Segment Advisor
 - The Segment Advisor performs its analysis by examining usage and growth statistics in the Automatic Workload Repository (AWR), and by sampling the data in the segment.
- Using the Segment Advisor
 - To use the Segment Advisor, check the results of Automatic Segment Advisor, and, optionally, run the Segment Advisor manually.
- Automatic Segment Advisor
 - The Automatic Segment Advisor is an automated maintenance task that is configured to run during all maintenance windows.
- Running the Segment Advisor Manually
 - You can manually run the Segment Advisor at any time with Cloud Control or with PL/SQL package procedure calls.
- Viewing Segment Advisor Results
 - The Segment Advisor creates several types of results: recommendations, findings, actions, and objects.
- Configuring the Automatic Segment Advisor
 - The Automatic Segment Advisor is an automated maintenance task. As such, you can use Cloud Control or PL/SQL package procedure calls to modify when (and if) this task runs. You can also control the resources allotted to it by modifying the appropriate resource plans.
- Viewing Automatic Segment Advisor Information
 You can query views to display information specific to the Automatic Segment Advisor.

18.3.2.1 About the Segment Advisor

The Segment Advisor performs its analysis by examining usage and growth statistics in the Automatic Workload Repository (AWR), and by sampling the data in the segment.

It is configured to run during maintenance windows as an automated maintenance task, and you can also run it on demand (manually). The Segment Advisor automated maintenance task is known as the Automatic Segment Advisor. You can use this information for capacity planning and for arriving at an informed decision about which segments to shrink.

The Segment Advisor generates the following types of advice:

- If the Segment Advisor determines that an object has a significant amount of free space, it
 recommends online segment shrink. If the object is a table that is not eligible for shrinking,
 as in the case of a table in a tablespace without automatic segment space management,
 the Segment Advisor recommends online table redefinition.
- If the Segment Advisor determines that a table could benefit from compression with the advanced row compression method, it makes a recommendation to that effect. (Automatic Segment Advisor only. See "Automatic Segment Advisor".)
- If the Segment Advisor encounters a table with row chaining above a certain threshold, it records that fact that the table has an excess of chained rows.



The Segment Advisor flags only the type of row chaining that results from updates that increase row length.

If you receive a space management alert, or if you decide that you want to reclaim space, you should start with the Segment Advisor.

18.3.2.2 Using the Segment Advisor

To use the Segment Advisor, check the results of Automatic Segment Advisor, and, optionally, run the Segment Advisor manually.

To use the Segment Advisor:

- Check the results of the Automatic Segment Advisor.
 - To understand the Automatic Segment Advisor, see "Automatic Segment Advisor", later in this section. For details on how to view results, see "Viewing Segment Advisor Results".
- 2. (Optional) Obtain updated results on individual segments by rerunning the Segment Advisor manually.

See "Running the Segment Advisor Manually", later in this section.

18.3.2.3 Automatic Segment Advisor

The Automatic Segment Advisor is an automated maintenance task that is configured to run during all maintenance windows.

The Automatic Segment Advisor does not analyze every database object. Instead, it examines database statistics, samples segment data, and then selects the following objects to analyze:

- Tablespaces that have exceeded a critical or warning space threshold
- Segments that have the most activity
- Segments that have the highest growth rate

In addition, the Automatic Segment Advisor evaluates tables that are at least 10MB and that have at least three indexes to determine the amount of space saved if the tables are compressed with the advanced row compression method.

If an object is selected for analysis but the maintenance window expires before the Segment Advisor can process the object, the object is included in the next Automatic Segment Advisor run.

You cannot change the set of tablespaces and segments that the Automatic Segment Advisor selects for analysis. You can, however, enable or disable the Automatic Segment Advisor task, change the times during which the Automatic Segment Advisor is scheduled to run, or adjust automated maintenance task system resource utilization. See "Configuring the Automatic Segment Advisor" for more information.

See Also:

- "Viewing Segment Advisor Results"
- Managing Automated Database Maintenance Tasks
- "Consider Using Table Compression" for more information on advanced row compression

18.3.2.4 Running the Segment Advisor Manually

You can manually run the Segment Advisor at any time with Cloud Control or with PL/SQL package procedure calls.

Reasons to manually run the Segment Advisor include the following:

- You want to analyze a tablespace or segment that was not selected by the Automatic Segment Advisor.
- You want to repeat the analysis of an individual tablespace or segment to get more up-todate recommendations.

You can request advice from the Segment Advisor at three levels:

- **Segment level**—Advice is generated for a single segment, such as an unpartitioned table, a partition or subpartition of a partitioned table, an index, or a LOB column.
- Object level—Advice is generated for an entire object, such as a table or index. If the
 object is partitioned, advice is generated on all the partitions of the object. In addition, if
 you run Segment Advisor manually from Cloud Control, you can request advice on the
 object's dependent objects, such as indexes and LOB segments for a table.
- **Tablespace level**—Advice is generated for every segment in a tablespace.

The <code>OBJECT_TYPE</code> column of Table 18-2 shows the types of objects for which you can request advice.

 Running the Segment Advisor Manually with Cloud Control You can run the Segment Advisor manually with Cloud Control Running the Segment Advisor Manually with PL/SQL
 You can run the Segment Advisor with the DBMS ADVISOR package.

18.3.2.4.1 Running the Segment Advisor Manually with Cloud Control

You can run the Segment Advisor manually with Cloud Control

You must have the <code>OEM_ADVISOR</code> role to run the Segment Advisor manually with Cloud Control. There are two ways to run the Segment Advisor:


Using the Segment Advisor Wizard

This method enables you to request advice at the tablespace level or object level. At the object level, you can request advice on tables, indexes, table partitions, and index partitions.

Using the Run Segment Advisor command on a schema object page.

For example, if you display a list of tables on the Tables page (accessible from the Schema menu), you can select a table and then select **Run Segment Advisor** from the Actions menu.

Figure 18-1 Tables page



This method enables you to include the schema object's dependent objects in the Segment Advisor run. For example, if you select a table and select **Run Segment Advisor**, Cloud Control displays the table's dependent objects, such as partitions, index segments, LOB segments, and so on. You can then select dependent objects to include in the run.

In both cases, Cloud Control creates the Segment Advisor task as an Oracle Database Scheduler job. You can schedule the job to run immediately, or can take advantage of advanced scheduling features offered by the Scheduler.

To run the Segment Advisor manually with the Segment Advisor Wizard:

- Access the Database Home page.
- From the Performance menu, select Advisors Home.

The Advisor Central page appears. (See Figure 18-2.)

Under Advisors, click Segment Advisor.

The first page of the Segment Advisor wizard appears.


Follow the wizard steps to schedule the Segment Advisor job, and then click Submit on the final wizard page.

The Advisor Central page reappears, with the new Segment Advisor job at the top of the list under the Results heading. The job status is SCHEDULED or RUNNING. (If you do not see your job, then use the search fields above the list to display it.)

5. Check the status of the job. If it is not COMPLETED, then use the **Refresh** control at the top of the page to refresh the page. (Do not use your browser's Refresh icon.)

When the job status changes to COMPLETED, select the job by clicking in the **Select** column, and then click **View Result**.

Figure 18-2 Advisor Central page



See Also:

Scheduling Jobs with Oracle Scheduler for more information about the advanced scheduling features of the Scheduler.

18.3.2.4.2 Running the Segment Advisor Manually with PL/SQL

You can run the Segment Advisor with the DBMS ADVISOR package.

You use package procedures to create a Segment Advisor task, set task arguments, and then execute the task. You must have the ADVISOR privilege. Table 18-1 shows the procedures that are relevant for the Segment Advisor. See *Oracle Database PL/SQL Packages and Types Reference* for more details on these procedures.

Table 18-1 DBMS_ADVISOR package procedures relevant to the Segment Advisor

Package Procedure Name	Description
CREATE_TASK	Use this procedure to create the Segment Advisor task. Specify 'Segment Advisor' as the value of the <code>ADVISOR_NAME</code> parameter.
Use this procedure to identify the target object for segment space adviparameter values of this procedure depend upon the object type. Table parameter values for each type of object.	
	Note: To request advice on an IOT overflow segment, use an object type of TABLE, TABLE PARTITION, or TABLE SUBPARTITION. Use the following query to find the overflow segment for an IOT and to determine the overflow segment table name to use with CREATE_OBJECT:
	<pre>select table_name, iot_name, iot_type from dba_tables;</pre>
SET_TASK_PARAMETER	Use this procedure to describe the segment advice that you need. Table 18-3 shows the relevant input parameters of this procedure. Parameters not listed here are not used by the Segment Advisor.
EXECUTE_TASK	Use this procedure to execute the Segment Advisor task.

Table 18-2 Input Parameters for DBMS_ADVISOR.CREATE_OBJECT

OBJECT_TYPE	ATTR1	ATTR2	ATTR3	ATTR4
TABLESPACE	tablespace name	NULL	NULL	Unused. Specify
TABLE	schema name	table name	NULL	Unused. Specify NULL.
INDEX	schema name	index name	NULL	Unused. Specify NULL.
TABLE PARTITION	schema name	table name	table partition name	Unused. Specify NULL.
INDEX PARTITION	schema name	index name	index partition name	Unused. Specify NULL.
TABLE SUBPARTITION	schema name	table name	table subpartition name	Unused. Specify NULL.
INDEX SUBPARTITION	schema name	index name	index subpartition name	Unused. Specify NULL.
LOB	schema name	segment name	NULL	Unused. Specify NULL.
LOB PARTITION	schema name	segment name	lob partition name	Unused. Specify NULL.
LOB SUBPARTITION	schema name	segment name	lob subpartition name	Unused. Specify

Table 18-3 Input for DBMS_ADVISOR.SET_TASK_PARAMETER

Input Parameter	Description	Possible Values	Default Value
time_limit	The time limit for the Segment Advisor run, specified in seconds.	Any number of seconds	UNLIMITED
recommend_all	Whether the Segment Advisor should generate findings for all segments.	TRUE: Findings are generated on all segments specified, whether or not space reclamation is recommended. FALSE: Findings are generated only for those objects that generate recommendations for space reclamation.	TRUE

Example

The example that follows shows how to use the DBMS_ADVISOR procedures to run the Segment Advisor for the sample table hr.employees. The user executing these package procedures must have the EXECUTE object privilege on the package or the ADVISOR system privilege.

Note that passing an object type of TABLE to DBMS_ADVISOR.CREATE_OBJECT amounts to an object level request. If the table is not partitioned, the table segment is analyzed (without any dependent segments like index or LOB segments). If the table is partitioned, the Segment Advisor analyzes all table partitions and generates separate findings and recommendations for each.

```
variable id number;
begin
  declare
  name varchar2(100);
  descr varchar2(500);
  obj id number;
  begin
  name:='Manual Employees';
  descr:='Segment Advisor Example';
  dbms advisor.create task (
    advisor name => 'Segment Advisor',
    task_id => :id,
task_name => name,
task_desc => descr);
  dbms advisor.create object (
    task_name => name,
object_type => 'TABLE',
attr1 => 'HR',
attr2 => 'EMPLOYEES',
     attr3
                        => NULL,
    attr3 => NULL,

attr4 => NULL,

attr5 => NULL,

object_id => obj_id);
  dbms_advisor.set_task_parameter(
     task_name => name,
     parameter
                       => 'recommend_all',
                       => 'TRUE');
     value
```

```
dbms_advisor.execute_task(name);
end;
end;
```

18.3.2.5 Viewing Segment Advisor Results

The Segment Advisor creates several types of results: recommendations, findings, actions, and objects.

You can view results in the following ways:

- With Cloud Control
- By querying the DBA_ADVISOR_* views
- By calling the DBMS SPACE.ASA RECOMMENDATIONS function

Table 18-4 describes the various result types and their associated DBA_ADVISOR_* views.

Table 18-4 Segment Advisor Result Types

Result Type	Associated View	Description
Recommendations	DBA_ADVISOR_RECOMMENDATI ONS	If a segment would benefit from a segment shrink, reorganization, or compression, the Segment Advisor generates a recommendation for the segment. Table 18-5 shows examples of generated findings and recommendations.
Findings	DBA_ADVISOR_FINDINGS	Findings are a report of what the Segment Advisor observed in analyzed segments. Findings include space used and free space statistics for each analyzed segment. Not all findings result in a recommendation. (There may be only a few recommendations, but there could be many findings.) When running the Segment Advisor manually with PL/SQL, if you specify 'TRUE' for recommend_all in the SET_TASK_PARAMETER procedure, then the Segment Advisor generates a finding for each segment that qualifies for analysis, whether or not a recommendation is made for that segment. For row chaining advice, the Automatic Segment Advisor generates findings only, and not recommendations. If the Automatic Segment Advisor has no space reclamation recommendations to make, it does not generate findings. However, the Automatic Segment Advisor may generate findings for tables that could benefit from advanced row compression.
Actions	DBA_ADVISOR_ACTIONS	Every recommendation is associated with a suggested action to perform: either segment shrink, online redefinition (reorganization), or compression. The DBA_ADVISOR_ACTIONS view provides either the SQL that you can use to perform a segment shrink or table compression, or a suggestion to reorganize the object.
Objects	DBA_ADVISOR_OBJECTS	All findings, recommendations, and actions are associated with an object. If the Segment Advisor analyzes multiple segments, as with a tablespace or partitioned table, then one entry is created in the <code>DBA_ADVISOR_OBJECTS</code> view for each analyzed segment. Table 18-2 defines the columns in this view to query for information on the analyzed segments. You can correlate the objects in this view with the objects in the findings, recommendations, and actions views.



- Viewing Segment Advisor Results with Cloud Control
 With Cloud Control, you can view Segment Advisor results for both Automatic Segment
 Advisor runs and manual Segment Advisor runs.
- Viewing Segment Advisor Results by Querying the DBA_ADVISOR_* Views
 You can view Segment Advisor results by querying the DBA_ADVISOR * views.
- Viewing Segment Advisor Results with DBMS_SPACE.ASA_RECOMMENDATIONS
 The ASA_RECOMMENDATIONS procedure in the DBMS_SPACE package returns a nested table object that contains findings or recommendations for Automatic Segment Advisor runs and, optionally, manual Segment Advisor runs.



Oracle Database PL/SQL Packages and Types Reference for details on the DBMS SPACE.ASA RECOMMENDATIONS function

18.3.2.5.1 Viewing Segment Advisor Results with Cloud Control

With Cloud Control, you can view Segment Advisor results for both Automatic Segment Advisor runs and manual Segment Advisor runs.

You can view the following types of results:

- All recommendations (multiple automatic and manual Segment Advisor runs)
- Recommendations from the last Automatic Segment Advisor run
- Recommendations from a specific run
- Row chaining findings

You can also view a list of the segments that were analyzed by the last Automatic Segment Advisor run.

To view Segment Advisor results with Cloud Control—All runs:

- Access the Database Home page.
- 2. From the Administration menu, select **Storage**, then **Segment Advisor**.

The Segment Advisor Recommendations page appears. Recommendations are organized by tablespace.

If any recommendations are present, select a tablespace, and then click Recommendation Details.

The Recommendation Details page appears. You can initiate the recommended activity from this page (shrink or reorganize).



Tip:

The list entries are sorted in descending order by reclaimable space. You can click column headings to change the sort order or to change from ascending to descending order.



To view Segment Advisor results with Cloud Control—Last Automatic Segment Advisor run:

- Access the Database Home page.
- 2. From the Administration menu, select **Storage**, then **Segment Advisor**.

The Segment Advisor Recommendations page appears. Recommendations are organized by tablespace.

The Segment Advisor Recommendations page appears.

- 3. In the View list, select Recommendations from Last Automatic Run.
- If any recommendations are present, select a tablespace and click Recommendation Details.

The Recommendation Details page appears. You can initiate the recommended activity from this page (shrink or reorganize).

To view Segment Advisor results with Cloud Control—Specific run:

- Access the Database Home page.
- From the Performance menu, select Advisors Home.

The Advisor Central page appears. (See Figure 18-2.)

- Check that your task appears in the list under the Results heading. If it does not, complete these steps:
 - a. In the Search section of the page, under Advisor Type, select **Segment Advisor**.
 - b. In the Advisor Runs list, select **All** or the desired time period.
 - c. (Optional) Enter a task name.
 - d. Click Go.

Your Segment Advisor task appears in the Results section.

- 4. Check the status of the job. If it is not COMPLETED, use the **Refresh** control at the top of the page to refresh the page. (Do not use your browser's Refresh icon.)
- Click the task name.

The Segment Advisor Task page appears, with recommendations organized by tablespace.

6. Select a tablespace in the list, and then click **Recommendation Details**.

The Recommendation Details page appears. You can initiate the recommended activity from this page (shrink or reorganize).

To view row chaining findings:

- Access the Database Home page.
- From the Administration menu, select Storage, then Segment Advisor.

The Segment Advisor Recommendations page appears. Recommendations are organized by tablespace.

The Segment Advisor Recommendations page appears.

3. Under the Related Links heading, click Chained Row Analysis.

The Chained Row Analysis page appears, showing all segments that have chained rows, with a chained rows percentage for each.



18.3.2.5.2 Viewing Segment Advisor Results by Querying the DBA ADVISOR * Views

You can view Segment Advisor results by querying the DBA_ADVISOR_* views.

The headings of Table 18-5 show the columns in the <code>DBA_ADVISOR_*</code> views that contain output from the Segment Advisor. See *Oracle Database Reference* for a description of these views. The table contents summarize the possible outcomes. In addition, Table 18-2 defines the columns in the <code>DBA_ADVISOR_OBJECTS</code> view that contain information on the analyzed segments.

Before querying the DBA_ADVISOR_* views, you can check that the Segment Advisor task is complete by querying the STATUS column in DBA ADVISOR TASKS.

The following example shows how to query the DBA_ADVISOR_* views to retrieve findings from all Segment Advisor runs submitted by user STEVE:

```
select af.task_name, ao.attr2 segname, ao.attr3 partition, ao.type, af.message
from dba_advisor_findings af, dba_advisor_objects ao
where ao.task_id = af.task_id
and ao.object_id = af.object_id
and ao.owner = 'STEVE';
```

TASK_NAME	SEGNAME	PARTITION	TYPE	MESSAGE
Manual_Employees	EMPLOYEES		TABLE	The free space in the obje ct is less than 10MB.
Manual_Salestable4	SALESTABLE4	SALESTABLE4_P1	TABLE PARTITION	Perform shrink, estimated savings is 74444154 bytes.
Manual_Salestable4	SALESTABLE4	SALESTABLE4_P2	TABLE PARTITION	The free space in the obje ct is less than 10MB.

Table 18-5 Segment Advisor Outcomes: Summary

MESSAGE column of DBA_ADVISOR_FINDINGS	MORE_INFO column of DBA_ADVISOR_FINDINGS	BENEFIT_TYPE column of DBA_ADVISOR_RECOMMEN DATIONS	ATTR1 column of DBA_ADVISOR_ACTIONS
Insufficient information to make a recommendation.	-	-	-
The free space in the object is less than 10MB.	Allocated Space:xxx: Used Space:xxx: Reclaimable Space:xxx	-	-
The object has some free space but cannot be shrunk because	Allocated Space:xxx: Used Space:xxx: Reclaimable Space:xxx	-	-

Table 18-5 (Cont.) Segment Advisor Outcomes: Summary

MESSAGE column of DBA_ADVISOR_FINDINGS	MORE_INFO column of DBA_ADVISOR_FINDINGS	BENEFIT_TYPE column of DBA_ADVISOR_RECOMMEN DATIONS	ATTR1 column of DBA_ADVISOR_ACTIONS
The free space in the object is less than the size of the last extent.	Allocated Space:xxx: Used Space:xxx: Reclaimable Space :xxx	-	-
Perform shrink, estimated savings is <i>xxx</i> bytes.	Allocated Space:xxx: Used Space:xxx: Reclaimable Space:xxx	Perform shrink, estimated savings is <i>xxx</i> bytes.	The command to execute. For example: ALTER object SHRINK SPACE;)
Enable row movement of the table <i>schema.table</i> and perform shrink, estimated savings is <i>xxx</i> bytes.	Allocated Space:xxx: Used Space:xxx: Reclaimable Space:xxx	Enable row movement of the table <i>schema.table</i> and perform shrink, estimated savings is <i>xxx</i> bytes	The command to execute. For example: ALTER object SHRINK SPACE;)
Perform re-org on the object <i>object</i> , estimated savings is <i>xxx</i> bytes.	Allocated Space:xxx: Used Space:xxx: Reclaimable Space:xxx	Perform re-org on the object <i>object</i> , estimated savings is <i>xxx</i> bytes.	Perform re-org
(Note: This finding is for objects with reclaimable space that are not eligible for online segment shrink.)			
The object has chained rows that can be removed by reorg.	xx percent chained rows can be removed by re-org.	-	-
Compress object object_name, estimated savings is xxx bytes. (This outcome is generated	Compress object object_name, estimated savings is xxx bytes.	-	The command to execute. For example: ALTER TABLE T1 ROW STORE COMPRESS ADVANCED
by the Automatic Segment Advisor only)			For this finding, see also the ATTR2 column of DBA_ADVISOR_ACTIONS.

18.3.2.5.3 Viewing Segment Advisor Results with DBMS_SPACE.ASA_RECOMMENDATIONS

The ASA_RECOMMENDATIONS procedure in the DBMS_SPACE package returns a nested table object that contains findings or recommendations for Automatic Segment Advisor runs and, optionally, manual Segment Advisor runs.

Calling this procedure may be easier than working with the DBA_ADVISOR_* views, because the procedure performs all the required joins for you and returns information in an easily consumable format.

The following query returns recommendations by the most recent run of the Auto Segment Advisor, with the suggested command to run to follow the recommendations:

```
select tablespace_name, segment_name, segment_type, partition_name, recommendations, c1 from table(dbms_space.asa_recommendations('FALSE', 'FALSE', 'FALSE'));

TABLESPACE_NAME SEGMENT_NAME SEGMENT_TYPE

PARTITION_NAME
```



RECOMMENDATIONS C.1 TVMDS ASSM ORDERS1 TABLE PARTITION ORDERS1 P2 Perform shrink, estimated savings is 57666422 bytes. alter table "STEVE". "ORDERS1" modify partition "ORDERS1 P2" shrink space TVMDS ASSM ORDERS1 TABLE PARTITION ORDERS1 P1 Perform shrink, estimated savings is 45083514 bytes. alter table "STEVE". "ORDERS1" modify partition "ORDERS1 P1" shrink space TVMDS ASSM NEW ORDERS NEW TARLE Perform shrink, estimated savings is 155398992 bytes. alter table "STEVE". "ORDERS NEW" shrink space TVMDS ASSM NEW ORDERS NEW INDEX INDEX Perform shrink, estimated savings is 102759445 bytes. alter index "STEVE". "ORDERS NEW INDEX" shrink space

See Oracle Database PL/SQL Packages and Types Reference for details on DBMS_SPACE.ASA_RECOMMENDATIONS.

18.3.2.6 Configuring the Automatic Segment Advisor

The Automatic Segment Advisor is an automated maintenance task. As such, you can use Cloud Control or PL/SQL package procedure calls to modify when (and if) this task runs. You can also control the resources allotted to it by modifying the appropriate resource plans.

You can call PL/SQL package procedures to make these changes, but the easier way to is to use Cloud Control.

To configure the Automatic Segment Advisor task with Cloud Control:

- Log in to Cloud Control as user SYSTEM.
- 2. Access the Database Home page.
- 3. From the Administration menu, select **Storage**, then **Segment Advisor**.

The Segment Advisor Recommendations page appears.

- 4. Under the Related Links heading, click the link entitled **Automated Maintenance Tasks**.
 - The Automated Maintenance Tasks page appears.
- Click Configure.

The Automated Maintenance Tasks Configuration page appears.



Automated Mainte Global Status (Enabled	enance Tasks Configura	ation		
Task Settings	Ŭ			
Optimizer Statistics Gathering Enabled Disabled Configure Segment Advisor Enabled Disabled Automatic SQL Tuning Enabled ODisabled Configure				
Maintenance Windo	w Group Assignment		Edit Window Group	
Window	Optimizer Statistics Gathering	Segment Advisor	Automatic SQL Tuning	
	Select All Select None	Select All Select None	Select All Select None	
MONDAY_WINDOW	▽	~		
TUESDAY_WINDOW	~	~		
WEDNESDAY_WINDOW	~	✓		
THURSDAY_WINDOW	~	~		
FRIDAY_WINDOW	~	~		
SATURDAY_WINDOW	~	~		

- 6. To completely disable the Automatic Segment Advisor, under Task Settings, select **Disabled** next to the Segment Advisor label, and then click **Apply**.
- 7. To disable the Automatic Segment Advisor for specific maintenance windows, clear the desired check boxes under the Segment Advisor column, and then click **Apply**.
- 8. To modify the start and end times and durations of maintenance windows, click **Edit Window Group**.

The Edit Window Group page appears. Click the name of a maintenance window, and then click **Edit** to change the window's schedule.

See Also:

Managing Automated Database Maintenance Tasks

18.3.2.7 Viewing Automatic Segment Advisor Information

You can query views to display information specific to the Automatic Segment Advisor.

View	Description
DBA_AUTO_SEGADV_SUMMARY	Each row of this view summarizes one Automatic Segment Advisor run. Fields include number of tablespaces and segments processed, and number of recommendations made.



View	Description
DBA_AUTO_SEGADV_CTL	Contains control information that the Automatic Segment Advisor uses to select and process segments. Each row contains information on a single object (tablespace or segment), including whether the object has been processed, and if so, the task ID under which it was processed and the reason for selecting it.

18.3.3 Shrinking Database Segments Online

You use online segment shrink to reclaim fragmented free space below the high water mark in an Oracle Database segment.

The benefits of segment shrink are these:

- Compaction of data leads to better cache utilization, which in turn leads to better online transaction processing (OLTP) performance.
- The compacted data requires fewer blocks to be scanned in full table scans, which in turns leads to better decision support system (DSS) performance.

Segment shrink is an online, in-place operation. DML operations and queries can be issued during the data movement phase of segment shrink. Concurrent DML operations are blocked for a short time at the end of the shrink operation, when the space is deallocated. Indexes are maintained during the shrink operation and remain usable after the operation is complete. Segment shrink does not require extra disk space to be allocated.

Segment shrink reclaims unused space both above and below the high water mark. In contrast, space deallocation reclaims unused space only above the high water mark. In shrink operations, by default, the database compacts the segment, adjusts the high water mark, and releases the reclaimed space.

Segment shrink requires that rows be moved to new locations. Therefore, you must first enable row movement in the object you want to shrink and disable any rowid-based triggers defined on the object. You enable row movement in a table with the ALTER TABLE ... ENABLE ROW MOVEMENT command.

Shrink operations can be performed only on segments in locally managed tablespaces with automatic segment space management (ASSM). Within an ASSM tablespace, all segment types are eligible for online segment shrink except these:

- IOT mapping tables
- Tables with rowid based materialized views
- Tables with function-based indexes
- SECUREFILE LOBS
- Tables compressed with the following compression methods:
 - Basic table compression using ROW STORE COMPRESS BASIC
 - Warehouse compression using COLUMN STORE COMPRESS FOR QUERY
 - Archive compression using COLUMN STORE COMPRESS FOR ARCHIVE

However, tables compressed with advanced row compression using ROW STORE COMPRESS ADVANCED are eligible for online segment shrink. See "Consider Using Table Compression" for information about table compression methods.



Note:

Shrinking database segments online might cause dependent database objects to become invalid. See "About Object Dependencies and Object Invalidation".

See Also:

Oracle Database SQL Language Reference for more information on the ALTER TABLE command.

Invoking Online Segment Shrink

Before invoking online segment shrink, view the findings and recommendations of the Segment Advisor. For more information, see "Using the Segment Advisor".

You invoke online segment shrink with Cloud Control or with SQL commands in SQL*Plus. The remainder of this section discusses the command line method.

Note:

You can invoke segment shrink directly from the Recommendation Details page in Cloud Control. Or, to invoke segment shrink for an individual table in Cloud Control, display the table on the Tables page, select the table, and then click **Shrink Segment** in the Actions list. (See Figure 18-1.) Perform a similar operation in Cloud Control to shrink indexes, materialized views, and so on.

You can shrink space in a table, index-organized table, index, partition, subpartition, materialized view, or materialized view log. You do this using ALTER TABLE, ALTER INDEX, ALTER MATERIALIZED VIEW, OR ALTER MATERIALIZED VIEW LOG Statement with the SHRINK SPACE clause.

Two optional clauses let you control how the shrink operation proceeds:

- The COMPACT clause lets you divide the shrink segment operation into two phases. When you specify COMPACT, Oracle Database defragments the segment space and compacts the table rows but postpones the resetting of the high water mark and the deallocation of the space until a future time. This option is useful if you have long-running queries that might span the operation and attempt to read from blocks that have been reclaimed. The defragmentation and compaction results are saved to disk, so the data movement does not have to be redone during the second phase. You can reissue the SHRINK SPACE clause without the COMPACT clause during off-peak hours to complete the second phase.
- The CASCADE clause extends the segment shrink operation to all dependent segments of the object. For example, if you specify CASCADE when shrinking a table segment, all indexes of the table will also be shrunk. (You need not specify CASCADE to shrink the partitions of a partitioned table.) To see a list of dependent segments of a given object, you can run the OBJECT DEPENDENT SEGMENTS procedure of the DBMS SPACE package.

As with other DDL operations, segment shrink causes subsequent SQL statements to be reparsed because of invalidation of cursors unless you specify the COMPACT clause.

Examples

Shrink a table and all of its dependent segments (including BASICFILE and SECUREFILE LOB segments):

ALTER TABLE employees SHRINK SPACE CASCADE;

Shrink a BASICFILE LOB segment only:

ALTER TABLE employees MODIFY LOB (perf review) (SHRINK SPACE);

Shrink a single partition of a partitioned table:

ALTER TABLE customers MODIFY PARTITION cust P1 SHRINK SPACE;

Shrink an IOT index segment and the overflow segment:

ALTER TABLE cities SHRINK SPACE CASCADE;

Shrink an IOT overflow segment only:

ALTER TABLE cities OVERFLOW SHRINK SPACE;

Shrink a SECUREFILE LOB segment and its partitions:

ALTER TABLE employees MODIFY LOB (sperf review) (SHRINK SPACE);

See Also:

- Oracle Database SQL Language Reference for the syntax and restrictions of the ALTER TABLE, ALTER INDEX, ALTER MATERIALIZED VIEW, and ALTER MATERIALIZED VIEW LOG statements with the SHRINK SPACE clause
- Oracle Database SecureFiles and Large Objects Developer's Guide for more information about LOB segments

18.3.4 Deallocating Unused Space

When you deallocate unused space, the database frees the unused space at the unused (high water mark) end of the database segment and makes the space available for other segments in the tablespace.

Before deallocation, you can run the <code>UNUSED_SPACE</code> procedure of the <code>DBMS_SPACE</code> package, which returns information about the position of the high water mark and the amount of unused space in a segment. For segments in locally managed tablespaces with automatic segment space management, use the <code>SPACE_USAGE</code> procedure for more accurate information on unused space.



See Also:

Oracle Database PL/SQL Packages and Types Reference contains the description of the $\tt DBMS_SPACE$ package

The following statements deallocate unused space in a segment (table, index or cluster):

```
ALTER TABLE table DEALLOCATE UNUSED KEEP integer;
ALTER INDEX index DEALLOCATE UNUSED KEEP integer;
ALTER CLUSTER cluster DEALLOCATE UNUSED KEEP integer;
```

The KEEP clause is optional and lets you specify the amount of space retained in the segment. You can verify that the deallocated space is freed by examining the DBA FREE SPACE view.

See Also:

- Oracle Database SQL Language Reference for details on the syntax and semantics of deallocating unused space
- Oracle Database Reference for more information about the DBA_FREE_SPACE view

18.4 Dropping Unused Object Storage

The <code>DBMS_SPACE_ADMIN</code> package includes the <code>DROP_EMPTY_SEGMENTS</code> procedure, which enables you to drop segments for empty tables and partitions that have been migrated from previous releases. This includes segments of dependent objects of the table, such as index segments, where possible.

The following example drops empty segments from every table in the database.

```
BEGIN
   DBMS_SPACE_ADMIN.DROP_EMPTY_SEGMENTS();
END:
```

The following drops empty segments from the HR. EMPLOYEES table, including dependent objects.

```
BEGIN
  DBMS_SPACE_ADMIN.DROP_EMPTY_SEGMENTS(
    schema_name => 'HR',
    table_name => 'EMPLOYEES');
END:
```

This procedure requires 11.2.0 or higher compatibility level.

See Also:

See Oracle Database PL/SQL Packages and Types Reference for details about this procedure

18.5 Understanding Space Usage of Data Types

When creating tables and other data structures, you must know how much space they will require. Each data type has different space requirements.

The Oracle Database PL/SQL Language Reference and Oracle Database SQL Language Reference contain extensive descriptions of data types and their space requirements.

18.6 Displaying Information About Space Usage for Schema Objects

Oracle Database provides data dictionary views and PL/SQL packages that allow you to display information about the space usage of schema objects.

- Using PL/SQL Packages to Display Information About Schema Object Space Usage
 A set of DBMS SPACE subprograms provide information about schema objects.
- Schema Objects Space Usage Data Dictionary Views
 A set of data dictionary views display information about space usage in schema objects.

18.6.1 Using PL/SQL Packages to Display Information About Schema Object Space Usage

A set of DBMS SPACE subprograms provide information about schema objects.

Package and Procedure/Function	Description
DBMS_SPACE.UNUSED_SPACE	Returns information about unused space in an object (table, index, or cluster).
DBMS_SPACE.FREE_BLOCKS	Returns information about free data blocks in an object (table, index, or cluster) whose segment free space is managed by free lists (segment space management is MANUAL).
DBMS_SPACE.SPACE_USAGE	Returns information about free data blocks in an object (table, index, or cluster) whose segment space management is AUTO.

See Also:

Oracle Database PL/SQL Packages and Types Reference for a description of the DBMS_SPACE package



Example: Using DBMS_SPACE.UNUSED_SPACE

The following SQL*Plus example uses the DBMS_SPACE package to obtain unused space information.

```
SQL> VARIABLE total blocks NUMBER
SQL> VARIABLE total bytes NUMBER
SQL> VARIABLE unused blocks NUMBER
SQL> VARIABLE unused bytes NUMBER
SQL> VARIABLE lastextf NUMBER
SQL> VARIABLE last extb NUMBER
SQL> VARIABLE lastusedblock NUMBER
SQL> exec DBMS_SPACE.UNUSED_SPACE('SCOTT', 'EMP', 'TABLE', :total_blocks, -
   :total bytes,:unused blocks, :unused bytes, :lastextf, -
   :last extb, :lastusedblock);
PL/SQL procedure successfully completed.
SOL> PRINT
TOTAL BLOCKS
TOTAL BYTES
_____
     10240
LASTUSEDBLOCK
```

18.6.2 Schema Objects Space Usage Data Dictionary Views

A set of data dictionary views display information about space usage in schema objects.

These views display information about space usage in schema objects:

View	Description	
DBA_SEGMENTS	DBA view describes storage allocated for all database segments. User	
USER_SEGMENTS	view describes storage allocated for segments for the current user.	
DBA_EXTENTS	DBA view describes extents comprising all segments in the database.	
USER_EXTENTS	User view describes extents comprising segments for the current user.	
DBA_FREE_SPACE	DBA view lists free extents in all tablespaces. User view shows free	
USER_FREE_SPACE	space information for tablespaces for which the user has quota.	

Example 1: Displaying Segment Information

You can query the DBA SEGMENTS view to display segment information.

Example 2: Displaying Extent Information

You can query the DBA_EXTENTS data dictionary view for information about the currently allocated extents in a database.

Example 3: Displaying the Free Space (Extents) in a Tablespace
 You can query the DBA_FREE_SPACE data dictionary view for information about the free extents (extents not allocated to any segment) in a database.

18.6.2.1 Example 1: Displaying Segment Information

You can query the DBA SEGMENTS view to display segment information.

The following query returns the name and size of each index segment in schema hr:

```
SELECT SEGMENT_NAME, TABLESPACE_NAME, BYTES, BLOCKS, EXTENTS
FROM DBA_SEGMENTS
WHERE SEGMENT_TYPE = 'INDEX'
AND OWNER='HR'
ORDER BY SEGMENT NAME;
```

The query output is:

SEGMENT_NAME	TABLESPACE_NAME	BYTES	BLOCKS	EXTENTS
COUNTRY_C_ID_PK	EXAMPLE	65536	32	1
DEPT_ID_PK	EXAMPLE	65536	32	1
DEPT_LOCATION_IX	EXAMPLE	65536	32	1
EMP_DEPARTMENT_IX	EXAMPLE	65536	32	1
EMP_EMAIL_UK	EXAMPLE	65536	32	1
EMP_EMP_ID_PK	EXAMPLE	65536	32	1
EMP_JOB_IX	EXAMPLE	65536	32	1
		65536	32	1
EMP_NAME_IX	EXAMPLE	65536	32	1
JHIST_DEPARTMENT_IX	EXAMPLE	65536	32	1
JHIST_EMPLOYEE_IX	EXAMPLE	65536	32	1
JHIST EMP ID ST DATE PK		65536	32	1
JHIST_JOB_IX	EXAMPLE	65536	32	1
JOB_ID_PK	EXAMPLE	65536	32	1
LOC_CITY_IX	EXAMPLE	65536	32	1
LOC_COUNTRY_IX	EXAMPLE	65536	32	1
LOC_COUNTRY_IX LOC_ID_PK	EXAMPLE	65536	32	1
LOC_STATE_PROVINCE_IX	EXAMPLE	65536	32	1
REG_ID_PK	EXAMPLE	65536	32	1

¹⁹ rows selected.

18.6.2.2 Example 2: Displaying Extent Information

You can query the DBA_EXTENTS data dictionary view for information about the currently allocated extents in a database.

For example, the following query identifies the extents allocated to each index segment in the hr schema and the size of each of those extents:

```
SELECT SEGMENT_NAME, SEGMENT_TYPE, TABLESPACE_NAME, EXTENT_ID, BYTES, BLOCKS
   FROM DBA_EXTENTS
   WHERE SEGMENT_TYPE = 'INDEX'
   AND OWNER='HR'
   ORDER BY SEGMENT NAME;
```

The query output is:

SEGMENT_NAME	SEGMENT_TYPE	TABLESPACE_NAME	EXTENT_ID	BYTES	BLOCKS
COUNTRY C ID PK	INDEX	EXAMPLE	0	65536	32

DEPT_ID_PK	INDEX	EXAMPLE	0	65536	32
DEPT_LOCATION_IX	INDEX	EXAMPLE	0	65536	32
EMP_DEPARTMENT_IX	INDEX	EXAMPLE	0	65536	32
EMP_EMAIL_UK	INDEX	EXAMPLE	0	65536	32
EMP_EMP_ID_PK	INDEX	EXAMPLE	0	65536	32
EMP_JOB_IX	INDEX	EXAMPLE	0	65536	32
EMP_MANAGER_IX	INDEX	EXAMPLE	0	65536	32
EMP_NAME_IX	INDEX	EXAMPLE	0	65536	32
JHIST_DEPARTMENT_IX	INDEX	EXAMPLE	0	65536	32
JHIST_EMPLOYEE_IX	INDEX	EXAMPLE	0	65536	32
JHIST_EMP_ID_ST_DATE_PK	INDEX	EXAMPLE	0	65536	32
JHIST_JOB_IX	INDEX	EXAMPLE	0	65536	32
JOB_ID_PK	INDEX	EXAMPLE	0	65536	32
LOC_CITY_IX	INDEX	EXAMPLE	0	65536	32
LOC_COUNTRY_IX	INDEX	EXAMPLE	0	65536	32
LOC_ID_PK	INDEX	EXAMPLE	0	65536	32
LOC_STATE_PROVINCE_IX	INDEX	EXAMPLE	0	65536	32
REG_ID_PK	INDEX	EXAMPLE	0	65536	32

19 rows selected.

For the hr schema, no segment has multiple extents allocated to it.

18.6.2.3 Example 3: Displaying the Free Space (Extents) in a Tablespace

You can query the DBA_FREE_SPACE data dictionary view for information about the free extents (extents not allocated to any segment) in a database.

For example, the following query reveals the amount of free space available as free extents in the SMUNDO tablespace:

```
SELECT TABLESPACE_NAME, FILE_ID, BYTES, BLOCKS
FROM DBA_FREE_SPACE
WHERE TABLESPACE NAME='SMUNDO';
```

The query output is:

TABLESPACE_NAME	FILE_ID	BYTES	BLOCKS
SMUNDO	3	65536	32
SMUNDO	3	65536	32
SMUNDO	3	65536	32
SMUNDO	3	65536	32
SMUNDO	3	65536	32
SMUNDO	3	65536	32
SMUNDO	3	131072	64
SMUNDO	3	131072	64
SMUNDO	3	65536	32
SMUNDO	3	3407872	1664

10 rows selected.

18.7 Capacity Planning for Database Objects

Oracle Database provides two ways to plan capacity for database objects: with Cloud Control or with the <code>DBMS_SPACE</code> PL/SQL package. Three procedures in the <code>DBMS_SPACE</code> package enable you to predict the size of new objects and monitor the size of existing database objects.

This documentation discusses the PL/SQL method. See Cloud Control online help and "Using the Segment Advisor" for details on capacity planning with Cloud Control.

Estimating the Space Use of a Table

The size of a database table can vary greatly depending on tablespace storage attributes, tablespace block size, and many other factors. The <code>CREATE_TABLE_COST</code> procedure of the <code>DBMS_SPACE</code> package lets you estimate the space use cost of creating a table.

Estimating the Space Use of an Index

The CREATE_INDEX_COST procedure of the DBMS_SPACE package lets you estimate the space use cost of creating an index on an existing table.

Obtaining Object Growth Trends

The <code>OBJECT_GROWTH_TREND</code> function of the <code>DBMS_SPACE</code> package produces a table of one or more rows, where each row describes the space use of the object at a specific time.

18.7.1 Estimating the Space Use of a Table

The size of a database table can vary greatly depending on tablespace storage attributes, tablespace block size, and many other factors. The <code>CREATE_TABLE_COST</code> procedure of the <code>DBMS_SPACE</code> package lets you estimate the space use cost of creating a table.

See Oracle Database PL/SQL Packages and Types Reference for details on the parameters of this procedure.

The procedure has two variants. The first variant uses average row size to estimate size. The second variant uses column information to estimate table size. Both variants require as input the following values:

- TABLESPACE_NAME: The tablespace in which the object will be created. The default is the SYSTEM tablespace.
- ROW COUNT: The anticipated number of rows in the table.
- PCT_FREE: The percentage of free space you want to reserve in each block for future expansion of existing rows due to updates.

In addition, the first variant also requires as input a value for AVG_ROW_SIZE, which is the anticipated average row size in bytes.

The second variant also requires for each anticipated column values for COLINFOS, which is an object type comprising the attributes COL_TYPE (the data type of the column) and COL_SIZE (the number of characters or bytes in the column).

The procedure returns two values:

- USED_BYTES: The actual bytes used by the data, including overhead for block metadata, PCT_FREE space, and so forth.
- ALLOC_BYTES: The amount of space anticipated to be allocated for the object taking into account the tablespace extent characteristics.



Note:

The default size of the first extent of any new segment for a partitioned table is 8 MB instead of 64 KB. This helps improve performance of inserts and queries on partitioned tables. Although partitioned tables will start with a larger initial size, once sufficient data is inserted, the space consumption will be the same as in previous releases. You can override this default by setting the INITIAL size in the storage clause for the table. This new default only applies to table partitions and LOB partitions.

18.7.2 Estimating the Space Use of an Index

The CREATE_INDEX_COST procedure of the DBMS_SPACE package lets you estimate the space use cost of creating an index on an existing table.

The procedure requires as input the following values:

- DDL: The CREATE INDEX statement that would create the index. The table specified in this DDL statement must be an existing table.
- [Optional] PLAN TABLE: The name of the plan table to use. The default is NULL.

The results returned by this procedure depend on statistics gathered on the segment. Therefore, be sure to obtain statistics shortly before executing this procedure. In the absence of recent statistics, the procedure does not issue an error, but it may return inappropriate results. The procedure returns the following values:

- USED BYTES: The number of bytes representing the actual index data.
- ALLOC BYTES: The amount of space allocated for the index in the tablespace.

18.7.3 Obtaining Object Growth Trends

The <code>OBJECT_GROWTH_TREND</code> function of the <code>DBMS_SPACE</code> package produces a table of one or more rows, where each row describes the space use of the object at a specific time.

The function retrieves the space use totals from the Automatic Workload Repository or computes current space use and combines it with historic space use changes retrieved from Automatic Workload Repository. See *Oracle Database PL/SQL Packages and Types Reference* for detailed information on the parameters of this function.

The function requires as input the following values:

- OBJECT OWNER: The owner of the object.
- OBJECT NAME: The name of the object.
- PARTITION_NAME: The name of the table or index partition, is relevant. Specify NULL otherwise.
- OBJECT TYPE: The type of the object.
- START TIME: A TIMESTAMP value indicating the beginning of the growth trend analysis.
- END_TIME: A TIMESTAMP value indicating the end of the growth trend analysis. The default is
 "NOW".



- INTERVAL: The length in minutes of the reporting interval during which the function should retrieve space use information.
- SKIP_INTERPOLATED: Determines whether the function should omit values based on recorded statistics before and after the INTERVAL ('YES') or not ('NO'). This setting is useful when the result table will be displayed as a table rather than a chart, because you can see more clearly how the actual recording interval relates to the requested reporting interval.

The function returns a table, each of row of which provides space use information on the object for one interval. If the return table is very large, the results are pipelined so that another application can consume the information as it is being produced. The output table has the following columns:

- TIMEPOINT: A TIMESTAMP value indicating the time of the reporting interval.
 - Records are not produced for values of TIME that precede the oldest recorded statistics for the object.
- SPACE USAGE: The number of bytes actually being used by the object data.
- SPACE ALLOC: The number of bytes allocated to the object in the tablespace at that time.
- QUALITY: A value indicating how well the requested reporting interval matches the actual recording of statistics. This information is useful because there is no guaranteed reporting interval for object size use statistics, and the actual reporting interval varies over time and from object to object.

The values of the OUALITY column are:

- GOOD: The value whenever the value of TIME is based on recorded statistics with a recorded timestamp within 10% of the INTERVAL specified in the input parameters.
 - INTERPOLATED: The value did not meet the criteria for GOOD, but was based on recorded statistics before and after the value of TIME. Current in-memory statistics can be collected across all instances in a cluster and treated as the "recorded" value for the present time.
 - PROJECTION: The value of TIME is in the future as of the time the table was produced. In an Oracle Real Application Clusters environment, the rules for recording statistics allow each instance to choose independently which objects will be selected.

The output returned by this function is an aggregation of values recorded across all instances in an Oracle RAC environment. Each value can be computed from a combination of GOOD and INTERPOLATED values. The aggregate value returned is marked GOOD if at least 80% of that value was derived from GOOD instance values.

