# An implementation of the SMite virtual machine for POSIX version 0.1

Reuben Thomas

23rd December 2018

# 1 Introduction

The SMite virtual machine [4] provides a portable virtual machine environment for study and experiment. To this end, SMite is itself written in ISO C, since almost all systems have an ISO C compiler available for them.

As well as the virtual machine, C SMite provides a debugger, which is described in [3].

The SMite virtual machine is described in [4]. This paper only describes the features specific to this implementation.

# 2 Using C SMite

This section describes how to compile C SMite, and the exact manner in which the interface calls and SMite's memory and registers should be accessed.

# 2.1 Configuration

SMite is written in ISO C99 using POSIX-1.2001 APIs.

The SMite virtual machine is inherently 32-bit, but will run happily on systems with larger (or smaller) addresses.

#### 2.2 Compilation

SMite's build system is written with GNU autotools, and the user needs only standard POSIX utilities to run it. Installation instructions are provided in the top-level file README.md.

### 2.3 Registers and memory

SMite's registers are declared in smite.h. Their names correspond to those given in [4, section 2.1], although some have been changed to meet the rules for C identifiers. C SMite does not allocate any memory for SMite, nor does it initialise any of the registers. C SMite provides the interface call **smite\_init()** to do this (see section 2.5).

The variables EP, I, A, MEMORY, SP, RP, HANDLER, BADPC and INVALID correspond exactly with the SMite registers they represent, and may be read and assigned to

accordingly, bearing in mind the restrictions on their use given in [4]. HANDLER, BADPC and INVALID are mapped into SMite's memory, so they are automatically updated when the corresponding memory locations are written to, and vice versa.

C SMite provides the ability to map native memory blocks into SMite's address space; see below.

#### 2.4 Extra instructions

C SMite provides some libraries of EXTRA instruction functions, which are called in general as:

Stack effect Description	
i*x u1 u2 j*x	Call the $u1$ th function of library $u2$ , passing arguments $i*x$ , with results $j*x$ .

Exception -259 is raised if an invalid library is accessed, and -260 for an invalid function in a known library.

#### 2.4.1 SMite

SMite provides access to its own API as library -1. This allows the current state to be controlled, or fresh states to be created and controlled.

Code	Name	Stack effect	Description
0x0	CURRENT_STATE	n-addr	a pointer to the current state
0x1	LOAD_WORD	n-addr a-addr x n	•
0x2	STORE_WORD	n-addr a-addr x n	
0x3	LOAD_BYTE	n-addr addr x n	
0x4	STORE_BYTE	n-addr addr x n	
0x5	PRE_DMA	${ t n-addr}$ ${ t a-addr}_1$ ${ t a-addr}_2$ ${ t f}$ ${ t n}$	
0x6	POST_DMA	${ t n-addr}$ ${ t a-addr}_1$ ${ t a-addr}_2$ ${ t n}$	
0x7	MEM_HERE	n-addr addr	
0x8	MEM_ALLOT	${ t n-addr_1}$ ${ t n-addr_2}$ ${ t u}$ ${ t f}$ ${ t addr}$	
0x9	MEM_ALIGN	n-addr addr	
0xa	NATIVE_ADDRESS	${ t n-addr}_1$ addr ${ t f}$ ${ t n-addr}_2$	
0xb	RUN	n-addr n	
0xc	SINGLE_STEP	n-addr n	
0xd	LOAD_OBJECT	n-addr fid addr n	
0xe	INIT	a-addr $u_1$ $u_2$ $u_3$ n-addr	
0xf	DESTROY	n-addr	
0x10	REGISTER_ARGS	n-addr n-addr n n	

# 2.4.2 Standard library

Standard C runtime and library functionality is accessed via library 0.

#### 2.4.2.1 Command-line arguments

Two calls are provided to access command-line arguments passed to C SMite (excluding any that it interprets itself). They are copied from Gforth ([2]).

Code	Name	Stack effect	Description
0x1	ARGC ARG_LEN ARG_COPY	u u1 u2 u <sub>1</sub> c-addr u <sub>2</sub> u <sub>3</sub>	the number of arguments the length of the $u1$ th argument copy argument $u_1$ to the buffer of length $u_2$ at $c$ -add $r$ , leaving the number of length $u_2$ at $u_3$ at $u_4$ leaving the number of length $u_4$ at $u_5$ and $u_6$ leaving the number of length $u_6$ at $u_6$ and $u_8$ leaving the number of length $u_8$ at $u_8$ at $u_9$ at $u_9$ at $u_9$ leaving the number of length $u_9$ at $u_9$ at $u_9$ leaving the number of length $u_9$ at $u_9$ at $u_9$ leaving the number of length $u_9$ at $u_9$ at $u_9$ leaving the number of length $u_9$ at $u_9$ leaving the number of length $u_9$ at $u_9$ length $u_9$ length $u_9$ at $u_9$ length $u_9$ leng

#### 2.4.2.2 Standard I/O streams

These extra instructions provide access to POSIX standard input, output and error. Each call returns a corresponding file identifier.

Opcode	POSIX file descriptor
0x3	STDIN_FILENO
0x4	STDOUT_FILENO
0x5	STDERR_FILENO

#### **2.4.2.3** File system

The file system extra instructions correspond directly to ANS Forth words, as defined in [1].

Opcode	Forth word
0x6	OPEN-FILE
0x7	CLOSE-FILE
0 <b>x</b> 8	READ-FILE
0 <b>x</b> 9	WRITE-FILE
0xa	FILE-POSITION
0xb	REPOSITION-FILE
0xc	FLUSH-FILE
0xd	RENAME-FILE
0xe	DELETE-FILE
0xf	FILE-SIZE
0x10	RESIZE-FILE
0x11	FILE-STATUS

The implementation-dependent word returned by FILE-STATUS contains the POSIX protection bits, given by the st\_mode member of the struct stat returned for the given file descriptor.

File access methods are bit-masks, composed as follows:

Bit value	Meaning
1	read
2	write
4	binary mode

To create a file, set both read and write bits to zero when calling OPEN-FILE.

# 2.5 Using the interface calls

The operation of the specified interface calls is given in [4]. Here, the C prototypes corresponding to the idealised prototypes used in [4] are given. The names are

prefixed with **smite**. The first argument to most routines is a @PACKAGE\_state \*, as returned by smite\_init.

Files to be loaded and saved are passed as C file descriptors. Thus, the calling program must itself open and close the files.

uint8\_t \*native\_address(smite\_state \*state, smite\_UWORD address, bool writable)

Returns NULL when the address is invalid, or the writable flag is true and the address is read-only.

smite\_state \*state, smite\_WORD run(smite\_state \*state)

The reason code returned by **smite\_run()** is a SMite word.

smite\_state \*state, smite\_WORD smite\_single\_step(smite\_state
\*state)

The reason code returned by **smite\_single\_step()** is a SMite word.

int smite\_load\_object(smite\_state \*state, int fd, smite\_UWORD
address)

If a file system error occurs, the return code is -3. If the endism of the object file does not match ENDISM, the return code is -4. If the word size of the object file is not WORD\_SIZE, the return code is -5. As an extension to the specification, if an object file starts with the bytes 35, 33 (#!), then it is assumed to be the start of a UNIX-style "hash bang" line, and the file contents up to and including the first newline character (10) is ignored.

In addition to the required interface calls C SMite provides an initialisation routine **smite\_init()** which, given a word array and its size, initialises SMite:

smite\_state smite\_init(size\_t memory\_size, size\_t data\_stack\_size, size\_t return\_stack\_size)

memory\_size is the size of b\_array in words (not bytes); similarly, data\_stack\_size and return\_stack\_size give the size of the stacks in words; these are allocated by smite\_init. The return value is NULL if memory cannot be allocated, and a pointer to a new state otherwise. All the registers are initialised as per [4].

The following routines give easier access to SMite's address space at the byte and word level. On success, they return 0, and on failure, the relevant exception code.

int smite\_load\_word(smite\_state \*state, smite\_UWORD address,
smite\_WORD \*value)

Load the word at the given address into the given smite\_WORD \*.

int smite\_store\_word(smite\_state \*state, smite\_UWORD address,
smite\_WORD value)

Store the given WORD value at the given address.

int smite\_load\_byte(smite\_state \*state, smite\_UWORD address,
smite\_BYTE \*value)

Load the byte at the given address into the given smite\_BYTE \*.

int smite\_store\_byte(smite\_state \*state, smite\_UWORD address,
smite\_BYTE value)

Store the given smite\_BYTE value at the given address.

The following routines give easier access to contiguous areas of SMite's address space. On success, 0 is returned; if to if not less than from, or the addresses are not contained in the same area, or not writable if desired, -1 is returned; if either address is unaligned, or some other error occurs, a memory exception code is returned.

int smite\_pre\_dma(smite\_state \*state, smite\_UWORD from, smite\_UWORD to, bool write)

Convert the given range to native byte order, so that it can be read (or written) directly.

int smite\_post\_dma(smite\_state \*state, smite\_UWORD from,
smite\_UWORD to)

Convert the given range to SMite byte order, so that it can be used by SMite after a direct access.

The following routines are provided to map system memory to SMite's address space and vice versa:

smite\_UWORD smite\_mem\_here(smite\_state \*state)

Returns the SMite address at which the next mapping will be made.

smite\_UWORD smite\_mem\_allot(smite\_state \*state, void \*p, size\_t n)
 Map n bytes pointed to by p into SMite's address space, and return the
 address mapped. Addresses are mapped sequentially.

smite\_UWORD smite\_mem\_align(smite\_state \*state)

Rounds up the address at which the next memory allocation will occur to the next word.

The following routine allows the calling program to register command-line arguments that can be retrieved by the ARGC and ARG\_COPY extra instructions.

int smite\_register\_args(smite\_state \*state, int argc, char
\*argv[])

Maps the given arguments register, which has the same format as that supplied to **main()**, into SMite's memory. Returns 0 on success and -1 if memory could not be allocated, or -2 if an argument could not be mapped to SMite's address space.

Programs which use C SMite's interface must #include the header file smite.h and be linked with the SMite library. smite\_opcodes.h, which contains an enumeration type of SMite's instruction set, and smite\_debug.h, which contains useful debugging functions such as disassembly, may also be useful; they are not documented here.

## 2.6 Other extras provided by C SMite

C SMite provides the following extra type in smite.h which is useful for programming with SMite:

smite\_WORD\_pointer: a union with members smite\_WORD words[smite\_NATIVE\_POINTER\_SIZE]
 and void (\*pointer)(void), which allow a function pointer suitable for the
 CALL\_NATIVE instruction to be easily stored and retrieved. It is assumed that
 the pointer is pushed on to the stack starting with words[0] and ending with
 words[smite\_NATIVE\_POINTER\_SIZE - 1].

# References

- [1] American National Standards Institute. ANS X3.215-1994: Programming Languages—Forth, 1994.
- [2] M. Anton Ertl, Bernd Paysan, Jens Wilke, Neal Crook, David Kühling, et al. Gforth. https://www.complang.tuwien.ac.at/forth/gforth/, 1993.
- [3] Reuben Thomas. A simple shell for the SMite Forth virtual machine, 2018. https://rrt.sc3d.org/.
- [4] Reuben Thomas. The SMite Forth virtual machine, 2018. https://rrt.sc3d.org/.