HLSL - Vertex Shader

Vertex Shader

The main thing that our vertex shader needs to do is convert the object space position from the mesh into a clip space position. This is required in order to correctly render fragments/pixels in the intended screen position.

In built-in shaders you would do this with the <code>UnityObjectToCLipPos</code> function, but this has been renamed to <code>TransformObjectToHCLip</code> (which you can find in the SRP-core <code>SpaceTransforms.hlsl</code>). That said, there's another way to handle the transform in URP as shown below which makes conversions to other spaces much easier too.

```
Varyings UnlitPassVertex(Attributes IN)
    Varyings OUT;
    // alternatively , Varyings OUT = (Varyings)0;
    // to initalise all struct inputs to 0.
    // otherwise, every variable in the struct must be set.
    // OUT.positionCS = TransformObjectToHClip(IN.positionOS.xyz);
    // Or :
    VertexPositionInputs positionInputs = GetVertexPositionInputs(IN.positionOS.xyz);
    OUT.positionCS = positionInputs.positionCS;
    // which also contains .positionWS, .positionVS and .positionNDS (aka screen position)
    // Pass through UV/TEXCOORD0 with texture tiling and offset ( BaseMap ST) applied :
    OUT.uv = TRANSFORM_TEX(IN.uv, _BaseMap);
    // Pass through Vertex Colours :
    OUT.color = IN.color;
    return OUT;
}
```

GetVertexPositionInputs computes the position in each of the commonly used spaces. It used to be a part of Core.hlsl, but was separated into it's own file - ShaderVariablesFunctions.hlsl in URP v9, but this file is automatically included when we include Core.hlsl anyway.

The function uses the object space postion from the *Attributes* as an input and returns a *VertexPositionInputs* struct, which contains:

- positionWS: the position in World space
- positionVS: the position in View space
- positionCS: the position in Clip space
- positionNDS: the position in **Normalised Device Coordinates**, aka Screen Position. (0, 0) in bottom left, (w, w) in top right. Of note, we would pass the position to the fragment stage, then handle the perspective divide (positionNDC.xy / positionNDC.w) so (1, 1) is top right instead.

For our current unlit shader, we don't need these other coordinate spaces, but this function is useful for shaders where we do. The unused ones also won't be included in the compiled shader so there isn't any unnecessary calculations.

The vertex shader is also responsible for passing data to the fragment , such as the texture coordinates (UV) and vertex colours . The values get interpolated across the triangle , as discussed in the Intro to Shaders post. For the UVs , we could just do out.uv = IN.uv; assuming both are set to float2 in the structs , but it's common to include the Tiling and Offset values for the texture which Unity passes into a float4 with the texture name + _ST (s referring to scale , and t for translate) . In this case , _BaseMap_ST which is also included in our UnityPerMaterial CBUFFER from earlier . In order to apply this to the UV , we could do:

```
OUT.uv = IN.uv * _BaseMap_ST.xy + _BaseMap_ST.zw;
```

But the TRANSFORM_TEX macro can also be used instead, which is included int the Built-in RP as well as URP.

While we don't need any normal/tangent data for our Unlit shader, there is also GetVertexNormalInputs which can obtain the World space position of the normal, tangent and generated bitangent vectors.

```
VertexNormalInputs normalInputs = GetVertexNormalInputs(IN.normalOS , IN.tangentOS);
OUT.normalWS = normalInputs.normalWS;
OUT.tangentWS = normalInputs.tangentWS;
OUT.bitangentWS = normalInputs.bitangentWS;
```

This will be useful later when Lighting is needed. There's also a version of the function which takes only the normalOS, which leaves tangentWS as (1,0,0) and bitangentWS as (0,1,0), or you could use positionWS = TransformObjectToWorldNormal(IN.normalOS) instead, which is useful if the tangent/bitangent isn't needed (e.g. No normal/bump or parallax mapping effects).