

# Eclipse GlassFish Reference Manual, Release 7

# Table of Contents

Eclipse GlassFish .....	1
Preface .....	2
1 Eclipse GlassFish 7 asadmin Utility Subcommands .....	4
add-library .....	5
add-resources .....	8
apply-http-lb-changes .....	12
attach .....	14
backup-domain .....	16
change-admin-password .....	18
change-master-broker .....	21
change-master-password .....	23
collect-log-files .....	25
configure-jms-cluster .....	28
configure-lb-weight .....	31
configure-ldap-for-admin .....	33
configure-managed-jobs .....	35
copy-config .....	37
create-admin-object .....	41
create-application-ref .....	44
create-audit-module .....	47
create-auth-realm .....	50
create-cluster .....	56
create-connector-connection-pool .....	66
create-connector-resource .....	72
create-connector-security-map .....	75
create-connector-work-security-map .....	78
create-context-service .....	81
create-custom-resource .....	84
create-domain .....	87
create-file-user .....	96
create-http .....	98
create-http-health-checker .....	101
create-http-lb .....	103
create-http-lb-config .....	107
create-http-lb-ref .....	110
create-http-listener .....	114

create-http-redirect .....	118
create-iiop-listener .....	120
create-instance .....	123
create-jacc-provider .....	131
create-javamail-resource .....	134
create-jdbc-connection-pool .....	137
create-jdbc-resource .....	149
create-jmsdest .....	152
create-jms-host .....	157
create-jms-resource .....	160
create-jndi-resource .....	165
create-jvm-options .....	168
create-lifecycle-module .....	173
create-local-instance .....	176
create-managed-executor-service .....	184
create-managed-scheduled-executor-service .....	188
create-managed-thread-factory .....	192
create-message-security-provider .....	195
create-module-config .....	199
create-network-listener .....	201
create-node-config .....	204
create-node-dcom .....	207
create-node-ssh .....	212
create-password-alias .....	217
create-profiler .....	219
create-protocol .....	222
create-protocol-filter .....	224
create-protocol-finder .....	226
create-resource-adapter-config .....	228
create-resource-ref .....	230
create-service .....	233
create-ssl .....	239
create-system-properties .....	243
create-threadpool .....	246
create-transport .....	249
create-virtual-server .....	253
delete-admin-object .....	261
delete-application-ref .....	263

delete-audit-module .....	266
delete-auth-realm .....	268
delete-cluster .....	270
delete-config .....	272
delete-connector-connection-pool .....	274
delete-connector-resource .....	276
delete-connector-security-map .....	279
delete-connector-work-security-map .....	281
delete-context-service .....	283
delete-custom-resource .....	285
delete-domain .....	287
delete-file-user .....	289
delete-http .....	291
delete-http-health-checker .....	293
delete-http-lb .....	295
delete-http-lb-config .....	297
delete-http-lb-ref .....	299
delete-http-listener .....	301
delete-http-redirect .....	303
delete-iiop-listener .....	305
delete-instance .....	307
delete-jacc-provider .....	309
delete-javamail-resource .....	312
delete-jdbc-connection-pool .....	314
delete-jdbc-resource .....	316
delete-jmsdest .....	318
delete-jms-host .....	320
delete-jms-resource .....	322
delete-jndi-resource .....	324
delete-jvm-options .....	326
delete-lifecycle-module .....	330
delete-local-instance .....	332
delete-managed-executor-service .....	335
delete-managed-scheduled-executor-service .....	337
delete-managed-thread-factory .....	339
delete-message-security-provider .....	341
delete-module-config .....	344
delete-network-listener .....	346

delete-node-config .....	348
delete-node-dcom .....	350
delete-node-ssh .....	353
delete-password-alias .....	356
delete-profiler .....	358
delete-protocol .....	360
delete-protocol-filter .....	362
delete-protocol-finder .....	364
delete-resource-adapter-config .....	366
delete-resource-ref .....	368
delete-ssl .....	370
delete-system-property .....	373
delete-threadpool .....	375
delete-transport .....	377
delete-virtual-server .....	379
deploy .....	381
deploydir .....	393
disable .....	402
disable-http-lb-application .....	404
disable-http-lb-server .....	406
disable-monitoring .....	408
disable-secure-admin .....	411
disable-secure-admin-internal-user .....	413
disable-secure-admin-principal .....	415
enable .....	417
enable-http-lb-application .....	419
enable-http-lb-server .....	421
enable-monitoring .....	423
enable-secure-admin .....	427
enable-secure-admin-internal-user .....	429
enable-secure-admin-principal .....	432
export .....	434
export-http-lb-config .....	437
export-sync-bundle .....	440
flush-connection-pool .....	443
flush-jmsdest .....	445
freeze-transaction-service .....	447
generate-jvm-report .....	449

get.....	453
get-active-module-config .....	457
get-client-stubs .....	459
get-health .....	461
import-sync-bundle .....	463
install-node .....	466
install-node-dcom.....	471
install-node-ssh.....	476
jms-ping .....	481
list.....	483
list-admin-objects.....	488
list-application-refs .....	490
list-applications.....	492
list-audit-modules.....	495
list-auth-realms.....	497
list-backups .....	499
list-batch-job-executions.....	502
list-batch-jobs .....	505
list-batch-job-steps .....	508
list-batch-runtime-configuration .....	511
list-clusters.....	514
list-commands .....	517
list-components.....	522
list-configs .....	525
list-connector-connection-pools .....	527
list-connector-resources .....	529
list-connector-security-maps .....	531
list-connector-work-security-maps .....	533
list-containers .....	535
list-context-services .....	537
list-custom-resources.....	539
list-domains .....	541
list-file-groups .....	543
list-file-users .....	545
list-http-lb-configs.....	547
list-http-lbs .....	549
list-http-listeners.....	552
list-iiop-listeners .....	554

list-instances . . . . .	556
list-jacc-providers . . . . .	561
list-javamail-resources . . . . .	563
list-jdbc-connection-pools . . . . .	565
list-jdbc-resources . . . . .	567
list-jmsdest . . . . .	569
list-jms-hosts . . . . .	572
list-jms-resources . . . . .	574
list-jndi-entries . . . . .	577
list-jndi-resources . . . . .	579
list-jobs . . . . .	581
list-jvm-options . . . . .	583
list-libraries . . . . .	586
list-lifecycle-modules . . . . .	588
list-log-attributes . . . . .	590
list-loggers . . . . .	592
list-log-levels . . . . .	594
list-managed-executor-services . . . . .	598
list-managed-scheduled-executor-services . . . . .	600
list-managed-thread-factories . . . . .	602
list-message-security-providers . . . . .	604
list-modules . . . . .	606
list-network-listeners . . . . .	608
list-nodes . . . . .	610
list-nodes-config . . . . .	613
list-nodes-dcom . . . . .	616
list-nodes-ssh . . . . .	619
list-password-aliases . . . . .	622
list-persistence-types . . . . .	624
list-protocol-filters . . . . .	627
list-protocol-finders . . . . .	629
list-protocols . . . . .	631
list-resource-adapter-configs . . . . .	633
list-resource-refs . . . . .	635
list-secure-admin-internal-users . . . . .	637
list-secure-admin-principals . . . . .	639
list-sub-components . . . . .	641
list-supported-cipher-suites . . . . .	643

list-system-properties .....	646
list-threadpools .....	648
list-timers .....	650
list-transports .....	652
list-virtual-servers .....	654
list-web-context-param .....	656
list-web-env-entry .....	659
login .....	662
migrate-timers .....	665
monitor .....	667
multimode .....	673
osgi .....	676
osgi-shell .....	680
ping-connection-pool .....	683
ping-node-dcom .....	686
ping-node-ssh .....	689
recover-transactions .....	692
redeploy .....	695
remove-library .....	704
restart-domain .....	707
restart-instance .....	710
restart-local-instance .....	713
restore-domain .....	717
rollback-transaction .....	719
rotate-log .....	721
set .....	723
set-batch-runtime-configuration .....	726
set-log-attributes .....	728
set-log-file-format .....	732
set-log-levels .....	734
setup-local-dcom .....	737
setup-ssh .....	740
set-web-context-param .....	745
set-web-env-entry .....	749
show-component-status .....	753
start-cluster .....	755
start-database .....	758
start-domain .....	762

start-instance .....	766
start-local-instance .....	770
stop-cluster .....	775
stop-database .....	778
stop-domain .....	780
stop-instance .....	783
stop-local-instance .....	786
undeploy .....	789
unfreeze-transaction-service .....	792
uninstall-node .....	794
uninstall-node-dcom .....	798
uninstall-node-ssh .....	802
unset .....	806
unset-web-context-param .....	808
unset-web-env-entry .....	811
update-connector-security-map .....	814
update-connector-work-security-map .....	817
update-file-user .....	819
update-node-config .....	821
update-node-dcom .....	823
update-node-ssh .....	827
update-password-alias .....	831
uptime .....	833
validate-dcom .....	835
validate-multicast .....	839
verify-domain-xml .....	842
version .....	844
2 Eclipse GlassFish 7 Utility Commands .....	847
appclient .....	848
asadmin .....	852
debug-asadmin .....	867
capture-schema .....	868
package-appclient .....	870
3 Eclipse GlassFish 7 Eclipse GlassFish Concepts .....	872
application .....	873
configuration .....	874
domain .....	875
dotted-names .....	876

instance.....	881
logging.....	882
monitoring.....	883
passwords.....	885
resource .....	886
security.....	887

# Eclipse GlassFish

Reference Manual

Release 7

Contributed 2018 - 2022

This reference manual describes administration commands and utility commands that are available with Eclipse GlassFish 7. This reference manual also describes concepts that are related to Eclipse GlassFish administration.

The available options, arguments, and operands for each command are provided in accordance with standard rules of command syntax, along with availability attributes, diagnostic information, and cross-references to other manual pages and reference material with relevant information.

This reference manual is for all users of Eclipse GlassFish.

---

Eclipse GlassFish Reference Manual, Release 7

Copyright © 2013, 2019 Oracle and/or its affiliates. All rights reserved.

This program and the accompanying materials are made available under the terms of the Eclipse Public License v. 2.0, which is available at <http://www.eclipse.org/legal/epl-2.0>.

SPDX-License-Identifier: EPL-2.0

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.



# Preface



This documentation is part of the Java Enterprise Edition contribution to the Eclipse Foundation and is not intended for use in relation to Java Enterprise Edition or Oracle GlassFish. The documentation is in the process of being revised to reflect the new Jakarta EE branding. Additional changes will be made as requirements and procedures evolve for Jakarta EE. Where applicable, references to Jakarta EE or Java Enterprise Edition should be considered references to Jakarta EE.

Please see the Title page for additional license information.

Both novice users and those familiar with Eclipse GlassFish can use online man pages to obtain information about the product and its features. A man page is intended to answer concisely the question "What does it do?" The man pages in general comprise a reference manual. They are not intended to be a tutorial.

## Overview

The following contains a brief description of each man page section and the information it references:

- Section 1 describes, in alphabetical order, the **asadmin** utility subcommands.
- Section 1M describes Eclipse GlassFish utility commands.
- Section 5ASC describes concepts that are related to Eclipse GlassFish administration.

Below is a generic format for man pages. The man pages of each manual section generally follow this order, but include only needed headings. For example, if there are no bugs to report, there is no Bugs section.

### Name

This section gives the names of the commands or functions documented, followed by a brief description of what they do.

### Synopsis

This section shows the syntax of commands or functions. The following special characters are used in this section:

**[ ]**

Brackets. The option or argument enclosed in these brackets is optional. If the brackets are omitted, the argument must be specified.

|

Separator. Only one of the arguments separated by this character can be specified at a time.

## Description

This section defines the functionality and behavior of the service. Thus it describes concisely what the command does. It does not discuss options or cite examples.

## Options

This section lists the command options with a concise summary of what each option does. The options are listed literally and in the order they appear in the Synopsis section. Possible arguments to options are discussed under the option, and where appropriate, default values are supplied.

## Operands

This section lists the command operands and describes how they affect the actions of the command.

## Examples

This section provides examples of usage or of how to use a command or function. Wherever possible a complete example including command-line entry and machine response is shown. Examples are followed by explanations, variable substitution rules, or returned values. Most examples illustrate concepts from the Synopsis, Description, Options, and Usage sections.

## Exit Status

This section lists the values the command returns to the calling program or shell and the conditions that cause these values to be returned. Usually, zero is returned for successful completion, and values other than zero for various error conditions.

## See Also

This section lists references to other man pages, in-house documentation, and outside publications.

## Notes

This section lists additional information that does not belong anywhere else on the page. It takes the form of an aside to the user, covering points of special interest. Critical information is never covered here.

## Bugs

This section describes known bugs and, wherever possible, suggests workarounds.

# 1 Eclipse GlassFish 7 asadmin Utility Subcommands

This section describes, in alphabetical order, the subcommands of the [asadmin\(1M\)](#) utility.

# add-library

Adds one or more library JAR files to Eclipse GlassFish

## Synopsis

```
asadmin [asadmin-options] add-library [--help]
[--type={common|ext|app}] [--upload={false|true}]
library-file-path [library-file-path ... ]
```

## Description

The **add-library** subcommand adds one or more library archive files to Eclipse GlassFish.

The **--type** option specifies the library type and the Eclipse GlassFish directory to which the library is added.

The library-file-path operand is the path to the JAR file that contains the library to be added. To specify multiple libraries, specify multiple paths separated by spaces.



The library archive file is added to the DAS. For common and extension libraries, you must restart the DAS so the libraries are picked up by the server runtime. To add the libraries to other server instances, synchronize the instances with the DAS by restarting them.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### **--help**

#### **-?**

Displays the help text for the subcommand.

#### **--type**

Specifies the library type and the Eclipse GlassFish directory to which the library is added. Valid values are as follows:

##### **common**

Adds the library files to the Common class loader directory, domain-dir/**lib**. This is the default.

**ext**

Adds the library files to the Java optional package directory, domain-dir/**lib/ext**.

**app**

Adds the library files to the application-specific class loader directory, domain-dir/**lib/applibs**.

For more information about these directories, see "[Class Loaders](#)" in Eclipse GlassFish Application Development Guide.

**--upload**

Specifies whether the subcommand uploads the file to the DAS. In most situations, this option can be omitted. Valid values are as follows:

**false**

The subcommand does not upload the file and attempts to access the file through the specified file name. If the DAS cannot access the file, the subcommand fails.

For example, the DAS might be running as a different user than the administration user and does not have read access to the file. In this situation, the subcommand fails if the **--upload** option is **false**.

**true**

The subcommand uploads the file to the DAS over the network connection.

The default value depends on whether the DAS is on the host where the subcommand is run or is on a remote host.

- If the DAS is on the host where the subcommand is run, the default is **false**.
- If the DAS is on a remote host, the default is **true**.

If a directory filepath is specified, this option is ignored.

## Operands

**library-file-path**

The paths to the archive files that contain the libraries that are to be added. You can specify an absolute path or a relative path.

If the **--upload** option is set to **true**, this is the path to the file on the local client machine. If the **--upload** option is set to **false**, this is the path to the file on the server machine.

## Examples

## Example 1 Adding Libraries

This example adds the library in the archive file `mylib.jar` to the application-specific class loader directory on the default server instance.

```
asadmin> add-library --type app /tmp/mylib.jar
Command add-library executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-libraries\(1\)](#), [remove-library\(1\)](#)

"[Class Loaders](#)" in Eclipse GlassFish Application Development Guide

# add-resources

Creates the resources specified in an XML file

## Synopsis

```
asadmin [asadmin-options] add-resources [--help]
[--target target]
[--upload={false|true}] xml-file-name
```

## Description

The **add-resources** subcommand creates the resources named in the specified XML file. The resources that can be created with this subcommand are listed in See Also in this help page.

The **--target** option specifies the target for which you are creating the resources. If this option specifies the domain, the resources are added only to the configuration of the domain administration server (DAS). If this option specifies any other target, the resources are added to the configuration of the DAS and references are added to the resources from the specified target.

The **xml-file-name** operand is the path to the XML file that contains the resources to be created. The **DOCTYPE** must be specified as [http://glassfish.org/dtds/glassfish-resources\\_1\\_5.dtd](http://glassfish.org/dtds/glassfish-resources_1_5.dtd) in the **resources.xml** file.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Specifies the target for which you are creating the resources.

Valid values are as follows:

#### server

Creates the resources for the default server instance **server** and is the default value.

**domain**

Creates the resources for the domain.

**cluster-name**

Creates the resources for every server instance in the cluster.

**instance-name**

Creates the resources for a particular Eclipse GlassFish instance.

**--upload**

Specifies whether the subcommand uploads the file to the DAS. In most situations, this option can be omitted. Valid values are as follows:

**false**

The subcommand does not upload the file and attempts to access the file through the specified file name. If the DAS cannot access the file, the subcommand fails.

For example, the DAS might be running as a different user than the administration user and does not have read access to the file. In this situation, the subcommand fails if the **--upload** option is **false**.

**true**

The subcommand uploads the file to the DAS over the network connection.

The default value depends on whether the DAS is on the host where the subcommand is run or is on a remote host.

- If the DAS is on the host where the subcommand is run, the default is **false**.
- If the DAS is on a remote host, the default is **true**.

# Operands

**xml-file-name**

The path to the XML file that contains the resources that are to be created. You can specify an absolute path, only the file name, or a relative path.

- If you specify an absolute path, the XML file can be anywhere.
- If you specify only the file name, the XML file must reside in the `domain-dir/config` directory on the DAS host. This requirement must be met even if you run the subcommand from another host.
- If you specify a relative path, the XML file must be in the relative directory.

An example XML file follows.

```

<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE resources PUBLIC
  "-//GlassFish.org//DTD GlassFish Application Server 3.1 Resource Definitions //EN"
  "http://glassfish.org/dtds/glassfish-resources_1_5.dtd">
<resources>
  <jdbc-connection-pool name="SPECjPool" steady-pool-size="100"
    max-pool-size="150" max-wait-time-in-millis="60000"
    pool-resize-quantity="2" idle-timeout-in-seconds="300"
    is-isolation-level-guaranteed="true"
    is-connection-validation-required="false"
    connection-validation-method="auto-commit"
    fail-all-connections="false"
    datasource-classname="oracle.jdbc.pool.OracleDataSource">
    <property name="URL"
      value="jdbc:oracle:thin:@iasperfsol12:1521:specdb"/>
    <property name="User" value="spec"/>
    <property name="Password" value="spec"/>
    <property name="MaxStatements" value="200"/>
    <property name="ImplicitCachingEnabled" value="true"/>
  </jdbc-connection-pool>
  <jdbc-resource enabled="true" pool-name="SPECjPool"
    jndi-name="jdbc/SPECjDB"/>
</resources>

```

## Examples

### Example 1 Adding Resources

This example creates resources using the contents of the XML file `resource.xml`.

```

asadmin> add-resources resource.xml
Command : Connector connection pool jms/testQFactoryPool created.
Command : Administered object jms/testQ created.
Command : Connector resource jms/testQFactory created.
Command : Resource adapter config myResAdapterConfig created successfully
Command : JDBC connection pool DerbyPoolA created successfully.
Command : JDBC resource jdbc/_defaultA created successfully.
Command add-resources executed successfully.

```

---

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jdbc-connection-pool\(1\)](#), [create-jdbc-resource\(1\)](#), [create-jms-resource\(1\)](#), [create-jndi-resource\(1\)](#), [create-javamail-resource\(1\)](#), [create-custom-resource\(1\)](#), [create-connector-resource\(1\)](#), [create-connector-work-security-map\(1\)](#), [create-admin-object\(1\)](#), [create-resource-adapter-config\(1\)](#)

# apply-http-lb-changes

Applies load balancer configuration changes to the load balancer

## Synopsis

```
asadmin [asadmin-options] apply-http-lb-changes [--help]  
lb-name
```

## Description

Use the [apply-http-lb-changes](#) subcommand to apply the changes in the load balancer configuration to the physical load balancer. The load balancer must already exist. To create a physical load balancer, use the [create-http-lb](#) subcommand.

This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

### Context

The Load Balancer distributes the workload among multiple Eclipse GlassFish instances , increasing the overall throughput of the system. The Load Balancer also enables requests to failover from one server instance to another. For HTTP session information to persist, configure HTTP session persistence.



The Load Balancer Plugin is only available with Eclipse GlassFish, and is not available with Eclipse GlassFish. For Eclipse GlassFish, it is possible to use the [mod\\_jk](#) module to configure load balancing on the Apache HTTP server.

For more information about configuring load balancing with Eclipse GlassFish, refer to the online help in the Eclipse GlassFish Administration Console.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

# Operands

## lb-name

The name of the load balancer to which changes are applied. The load balancer must already exist. You can create it with the [create-http-lb](#) subcommand.

# Examples

## Example 1 Using the [apply-http-lb-changes](#) subcommand

This example applies configuration changes to a load balancer named `mylb`.

```
asadmin> apply-http-lb-changes mylb
Command apply-http-lb-changes executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-http-lb\(1\)](#), [create-http-lb-config\(1\)](#)

# attach

Attaches to subcommands that were started using `asadmin --detach` or that contain progress information

## Synopsis

```
asadmin [asadmin-options] attach [--help]
job_id
```

## Description

The `attach` subcommand attaches to subcommands that were started using the `asadmin` utility option `--detach` or that contain progress information. The `--detach` option detaches long-running subcommands and executes them in the background in detach mode.

Job IDs are assigned to the subcommands (jobs), and can be used to view the status of a job and its output. Use the `list-jobs(1)` subcommand to view the jobs and their job IDs, and the `configure-managed-jobs(1)` subcommand to configure how long information about the jobs is kept.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### job\_id

The ID of the job for which you want to view status and output.

## Examples

## Example 1 Attaching to a Subcommand and Checking Its Status

This example attaches to the `deploy` subcommand with a job ID of `20` and shows that the job is finished. If a subcommand is still in progress, the output displays the current status, for example, `64%: Uploading bits`.

```
asadmin> attach 20
Finished execution of deploy
Command attach executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[configure-managed-jobs\(1\)](#), [list-jobs\(1\)](#)

# backup-domain

Performs a backup on the domain

## Synopsis

```
asadmin [asadmin-options] backup-domain [--help]
[--long[={false|true}]]
[--description description-text]
[--domainmdir domain-root-dir]
[--backupdir backup-directory]
[--backupconfig backup-config-name]
[domain_name]
```

## Description

The **backup-domain** subcommand backs up files under the named domain.

This subcommand is supported in local mode only in Eclipse GlassFish, and is supported in local mode and remote mode in Eclipse GlassFish.

In Eclipse GlassFish, the domain to be backed up must be stopped.

In Eclipse GlassFish, the domain to be backed up must be stopped or be suspended using the **suspend-domain(1)** subcommand.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the **asadmin(1M)** help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--long**

**-l**

Displays detailed information about the backup operation.

The default value is 'false'.

### --description

Specifies a description to store in the backup file. The description is displayed as part of the information about a backup file.

The default value has this form:

```
domain-name backup created on YYYY_MM_DD by user user-name
```

### --domaindir

Specifies the domain root directory, the parent directory of the domain to back up.

The default value is as-install/[domains](#).

### --backupdir

Specifies the directory under which the backup file is to be stored.

The default value is as-install/[domains](#)/domain-dir/[backups](#). If the domain is not in the default location, the location is domain-dir/[backups](#).

### --backupconfig

(Supported only in Eclipse GlassFish.) The name of the domain backup configuration in the backup directory under which the backup file is to be stored.

## Operands

### domain-name

Specifies the name of the domain to be backed up.

This operand is optional if only one domain exists in the Eclipse GlassFish installation.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-backups\(1\)](#), [restore-domain\(1\)](#), [resume-domain\(1\)](#), [suspend-domain\(1\)](#)

# change-admin-password

Changes the administrator password

## Synopsis

```
asadmin [asadmin-options] change-admin-password [--help]
[--domaindir domain-root-dir [--domain_name domain-name]]
```

## Description

The `change-admin-password` subcommand modifies the administrator password. The `change-admin-password` subcommand is interactive because the subcommand prompts the user for the old administrator password, for the new administrator password, and for confirmation of the new administrator password. The new password must contain at least 8 characters.

If the only user is an anonymous user without a password, this subcommand fails.

If a blank password is provided, this subcommand fails if secure administration is enabled.

For security purposes, create a password-protected user account with administrator privileges. To create this account, use the `create-file-user(1)` or the Administration Console. After creating this user account, remove the anonymous user to restrict access to Eclipse GlassFish settings.

If more than one administrator is configured for Eclipse GlassFish, you must run the `asadmin` command with the `--user` option to change the password for that user. For more information, see the examples in this help page.

This subcommand is supported in local mode and remote mode. If the `--domaindir` or `--domain_name` option is specified, the `change-admin-password` subcommand operates in local mode. If neither option is specified, the `change-admin-password` subcommand first attempts to operate in remote mode. If neither option is specified and the DAS is not running, the `change-admin-password` subcommand operates in local mode, using the default values for the `--domaindir` and `--domain_name` options.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--domaindir**

Specifies the parent directory of the domain specified in the `--domain_name` option. When this option is used, the `change-admin-password` subcommand operates in local mode.

**--domain\_name**

Specifies the domain of the admin user.

This option is not required if the directory specified by the `--domaindir` option contains only one domain.

## Examples

### Example 1 Changing the Administrator Password For a Single User in Multimode

```
asadmin --user admin
asadmin> change-admin-password
Please enter the old admin password>
Please enter the new admin password>
Please enter the new admin password again>
Command change-admin-password executed successfully.
```

### Example 2 Changing the Administrator Password For a Single User in Single Mode

```
asadmin --user admin change-admin-password
Please enter the old admin password>
Please enter the new admin password>
Please enter the new admin password again>
Command change-admin-password executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

command failed

## See Also

[asadmin\(1M\)](#)

[create-file-user\(1\)](#), [delete-password-alias\(1\)](#), [list-password-aliases\(1\)](#), [update-password-alias\(1\)](#)

# change-master-broker

Changes the master broker in a Message Queue cluster providing JMS services for a Eclipse GlassFish cluster.

## Synopsis

```
asadmin [asadmin-options] change-master-broker [--help]
clustered-instance-name
```

## Description

The **change-master-broker** subcommand changes the master broker in a Message Queue cluster that is the JMS provider for a Eclipse GlassFish cluster. By default, the master broker is the one associated with the first instance configured in the Eclipse GlassFish cluster.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

## Operands

### clustered-instance-name

The name of the server instance whose Message Queue broker is to become the master broker of the Message Queue cluster. This server instance must be an instance in a Eclipse GlassFish cluster.

## Examples

### Example 1 Changing the master broker

The following subcommand changes the Message Queue master broker to the one for the **clustinst3**

clustered instance.

```
asadmin> change-master-broker clustinst3  
Command change-master-broker executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

# change-master-password

Changes the master password

## Synopsis

```
asadmin [asadmin-options] change-master-password [--help]
[--nodedir node-dir] [--domaindir domain-dir]
[--savemasterpassword={false|true}] [domain-name|node-name]
```

## Description

The **change-master-password** subcommand is used to modify the master password. The **change-master-password** subcommand is interactive in that the user is prompted for the old master password, as well as the new master password. This subcommand will not work unless the server is stopped. In a distributed environment, this command must run on each machine in the domain.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --nodedir

The name of the directory containing the node instance for which the password will be changed. If this option is omitted, the change is applied to the entire domain.

#### --domaindir

The name of the domain directory used for this operation. By default, the **--domaindir** option is **\$AS\_DEF\_DOMAINS\_PATH**, which is an environment variable defined in the file **asenv.bat** or **asenv.conf**.

#### --savemasterpassword

This option indicates whether the master password should be written to the file system. This is necessary so that the **start-domain(1)** command can start the server without having to prompt the user.

The default is **false**.



Saving the master password on disk is extremely insecure and should be avoided.



If the `--savemasterpassword` option is not set, the master password file, if it exists, will be deleted.

## Operands

### domain-name|node-name

This name of the domain or node for which the password will be changed. If there is only a single domain, this is optional.

## Examples

### Example 1 Changing the Master Password

This example shows how to change the master password for the `domain44ps` domain.

```
asadmin>change-master-password domain44ps
Please enter the new master password>
Please enter the new master password again>
Master password changed for domain44ps
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-password-alias\(1\)](#), [list-password-aliases\(1\)](#), [start-domain\(1\)](#), [update-password-alias\(1\)](#)

# collect-log-files

Creates a ZIP archive of all available log files

## Synopsis

```
asadmin [asadmin-options] collect-log-files [--help]
[--target target]
[--retrieve={false|true}] [retrievefilepath]]
```

## Description

The **collect-log-files** subcommand collects all available log files for the domain administration server (DAS), the specified cluster, or the specified Eclipse GlassFish instance and creates a single ZIP archive of the log files. If a cluster is specified, the ZIP archive also contains the log file for the DAS.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--retrieve**

Specifies whether the ZIP archive is created in a directory other than the default directory.

By default the ZIP archive is created in the domain-dir`/collected-logs` directory. The ZIP file names are constructed from the specified target and timestamp, as follows:

```
log_YYYY-MM-DD_HH-MIN-SEC.zip
```

Possible values are as follows:

**false**

The ZIP archive will be created in the default directory. If omitted, the **--retrieve** option defaults to **false**.

**true**

The ZIP archive will be created in the directory that the `retrievefilepath` operand specifies. If `retrievefilepath` is omitted, the ZIP archive will be created in the default directory.

**--target**

Specifies the target for which log files will be collected.

Possible values are as follows:

**server**

The log files will be collected for the DAS (default).

**instance-name**

The log files will be collected for the specified Eclipse GlassFish instance.

**cluster-name**

The log files will be collected for the specified cluster and the DAS.

# Operands

## retrievefilepath

The name of the directory in which the ZIP archive will be created. If this operand is omitted, the ZIP archive will be created in the default directory. If the `--retrieve` option is `false`, this operand is ignored.

# Examples

## Example 1 Collecting Log Files for the Default Server

This example generates a ZIP archive from the log files for the default server.

```
asadmin> collect-log-files
Created Zip file under /space/gf/glassfish7/glassfish/domains/domain1/\
collected-logs/log_2021-12-15_15-46-23.zip.
Command collect-log-files executed successfully.
```

## Example 2 Collecting Log Files for a Cluster

This example generates a ZIP archive from the log files for a cluster named `cluster1` and the two server instances running in the cluster.

```
asadmin> collect-log-files --target cluster1
Log files are downloaded for instance1.
Log files are downloaded for instance2.
Created Zip file under /space/gfv/glassfish7/glassfish/domains/domain1/\
collected-logs/log_2021-12-15_15-54-06.zip.
Command collect-log-files executed successfully.
```

## Example 3 Collecting Log Files in a Directory Other Than the Default for a Cluster

This example generates a ZIP archive from the log files for a cluster named `cluster1` and its two server instances, and saves the archive in a directory named `/space/output`.

```
asadmin> collect-log-files --target cluster1 --retrieve true /space/output
Log files are downloaded for instance1.
Log files are downloaded for instance2.
Created Zip file under /space/output/log_2010-12-15_15-55-54.zip.
Command collect-log-files executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-log-attributes\(1\)](#), [list-log-levels\(1\)](#), [rotate-log\(1\)](#), [set-log-attributes\(1\)](#), [set-log-levels\(1\)](#)

"[Administering the Logging Service](#)" in Eclipse GlassFish Administration Guide

# configure-jms-cluster

Configures the Message Queue cluster providing JMS services to a Eclipse GlassFish cluster

## Synopsis

```
asadmin [asadmin-options] configure-jms-cluster [--help]
[--clustertype={conventional|enhanced}]
[--configstoretype={masterbroker|shareddb}]
[--messagestoretype={file|jdbc}]
[--dbvendor database-vendor]
[--dbuser database-user]
[--dburl database-url]
[--property (name=value)[:name=value]*]
cluster-name
```

## Description

The **configure-jms-cluster** configures the Message Queue cluster providing JMS services to a Eclipse GlassFish cluster.

This subcommand should be used before the Eclipse GlassFish cluster is started for the first time. Otherwise, follow the instructions in "[Administering the Java Message Service \(JMS\)](#)" in Eclipse GlassFish Administration Guide.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --clustertype

The type of Message Queue cluster to configure. The value **conventional** specifies a conventional cluster, and the value **enhanced** specifies an enhanced, high-availability cluster. For information about these cluster types of Message Queue clusters, see "[Broker Clusters](#)" in Open Message Queue Technical Overview.

The default value is `conventional`.

If `enhanced` is specified, the `configstoretype` and `messagestoretype` options are ignored.

#### **--configstoretype**

The type of data store for configuration data in a conventional cluster. The value `masterbroker` specifies the use of a master broker to store and manage the configuration data. The value `shareddb` specifies the use of a shared database to store the configuration data.

The default value is `masterbroker`.

This option is ignored if `clustertype` is set to `enhanced`.

#### **--messagestoretype**

The type of data store for message data in brokers in a conventional cluster. The value `file` specifies a file store. The value `jdbc` specifies a JDBC store.

The default value is `file`.

This option is ignored if `clustertype` is set to `enhanced`.

#### **--dbvendor**

#### **--dbuser**

#### **--dburl**

The database vendor, user, and access url of the JDBC database to use in any of these situations:

- When `clustertype` is set to `enhanced`
- When `configstoretype` is set to `shareddb`
- When `messagestoretype` is set to `jdbc`

For information about supported vendors and the formats of access urls for each vendor, see "[JDBC-Based Persistence](#)" in Open Message Queue Administration Guide.



To specify the password of the JDBC database user, use the `--passwordfile` utility option of the `asadmin(1M)` command after adding the entry `AS_ADMIN_JMSDBPASSWORD` to the password file.

#### **--property**

A list of additional database-vendor-specific properties to configure the JDBC database for use by the Message Queue cluster. Specify properties as a colon (`:`) separated list of property names and values in the form:

```
prop1name=prop1value:prop2name=prop2value
```

# Operands

**cluster-name**

The name of the Eclipse GlassFish cluster for which the Message Queue cluster is to provide JMS services.

Because Eclipse GlassFish uses the cluster name to uniquely identify database tables the Message Queue cluster might require, the length of the name is restricted in the following situations:

- If `clustertype` is set to `enhanced`, the name can be no longer than n–21 characters, where n is the maximum table name length allowed by the database.
- If `configstoretype` is set to `shareddb`, the name can be no longer than n–19 characters, where n is the maximum table name length allowed by the database.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

# configure-lb-weight

Sets load balancing weights for clustered instances

## Synopsis

```
asadmin [asadmin-options] configure-lb-weight [--help]
--cluster cluster_name
instance-name=weight[:instance-name=weight]
```

## Description

The **configure-lb-weight** subcommand assigns weight to the server instances in a cluster. Weights can be used for HTTP, RMI/IOP and JMS load balancing. For the HTTP load balancer, the weights are used only if the load balancer's policy is set to **weighted-round-robin**. The load balancer policy is set in the **create-http-lb-ref** subcommand or **set** subcommand.

Use the weight to vary the load going to different instances in the cluster. For example, if an instance is on a machine with more capacity, give it a higher weight so that more requests are sent to that instance by the load balancer. The default weight is 100. If all instances have the default weight, the load balancer performs simple round robin load balancing.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--cluster**

The name of the cluster.

## Operands

### instance-name=weight

The name of the instance and the weight you are assigning it. The weight must be an integer. The

pairs of instances and weights are separated by colons. For example `instance1=1:instance2=4` means that for every five requests, one goes to instance1 and four go to instance2. A weight of 1 is the default.

## Examples

### Example 1 Assigning Load Balancer Weights to Cluster Instances

The following subcommand assigns weights of 1, 1, and 2 to instances `i1`, `i2`, and `i3` in the `cluster1` cluster.

```
asadmin> configure-lb-weight --cluster cluster1 i1=1:i2=1:i3=2
Command configure-lb-weight executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb-ref\(1\)](#)[create-cluster\(1\)](#)

# configure-ldap-for-admin

Configures the authentication realm named admin-realm for the given LDAP

## Synopsis

```
asadmin [asadmin-options] configure-ldap-for-admin [--help]
```

## Description

The `configure-ldap-for-admin` subcommand configures the authentication realm named `admin-realm` for the given LDAP. The `configure-ldap-for-admin` subcommand is interactive. The subcommand prompts the user for the `basedn` and `ldap-group` options.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Examples

### Example 1 Configuring the LDAP Authentication Realm

```
asadmin> configure-ldap-for-admin
Enter the value for the basedn option>
Enter the value for the ldap-group option>
The LDAP Auth Realm admin-realm was configured correctly
in admin server's configuration.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[change-admin-password\(1\)](#), [create-auth-realm\(1\)](#)[create-auth-realm\(1\)](#), [list-auth-realms\(1\)](#)

# configure-managed-jobs

Configures how long information about subcommands that were started using `asadmin --detach` or that contain progress information is kept

## Synopsis

```
asadmin [asadmin-options] configure-managed-jobs [--help]
[--in-memory-retention-period in-memory-retention-period]
[--job-retention-period job-retention-period]
[--cleanup-initial-delay cleanup-initial-delay]
[--cleanup-poll-interval cleanup-poll-interval]
```

## Description

The `configure-managed-jobs` subcommand configures how long information about subcommands (jobs) that were started using the `asadmin` utility option `--detach` or that contain progress information is kept. The `--detach` option detaches long-running subcommands and executes them in the background in detach mode. Job information includes subcommand progress and status.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### `--help`

`-?`

Displays the help text for the subcommand.

#### `--in-memory-retention-period`

Specifies how long a completed job is kept in memory after the job is finished. The default value is 1 hour.

#### `--job-retention-period`

Specifies how long a job is stored. The default value is 24 hours.

#### `--cleanup-initial-delay`

After server startup, specifies the initial delay after which the cleanup service starts purging jobs. The default value is 5 minutes.

**--cleanup-poll-interval**

Specifies the time interval after which the cleanup service polls for expired jobs. The default value is 20 minutes.

## Examples

### Example 1 Configuring the Job Retention Period

This example sets the job retention period to 36 hours. Time periods can be specified in Hh|Mm|Ss for hours, minutes, or seconds.

```
asadmin> configure-managed-jobs --job-retention-period=36h
Command configure-managed-jobs executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-jobs\(1\)](#)

# copy-config

Copies an existing named configuration to create another configuration

## Synopsis

```
asadmin [asadmin-options] copy-config [--help]
[--systemproperties (name=value)[:name=value]*]
source-configuration-name destination-configuration-name
```

## Description

The **copy-config** subcommand creates a named configuration in the configuration of the domain administration server (DAS) by copying an existing configuration. The new configuration is identical to the copied configuration, except for any properties that you specify in the **--systemproperties** option.

The **default-config** configuration is copied when a standalone sever instance or standalone cluster is created.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --systemproperties

Optional attribute name-value pairs for the configuration. These properties override port settings in the configuration.

The following properties are available:

#### **ASADMIN\_LISTENER\_PORT**

This property specifies the port number of the HTTP port or HTTPS port through which the DAS connects to the instance to manage the instance. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **HTTP\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTP requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **HTTP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTPS requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **IIOP\_LISTENER\_PORT**

This property specifies the port number of the port that is used for IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **IIOP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **IIOP\_SSL\_MUTUALAUTH\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections with client authentication. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **JAVA\_DEBUGGER\_PORT**

This property specifies the port number of the port that is used for connections to the Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugger. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **JMS\_PROVIDER\_PORT**

This property specifies the port number for the Java Message Service provider. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **JMX\_SYSTEM\_CONNECTOR\_PORT**

This property specifies the port number on which the JMX connector listens. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

### **OSGI\_SHELL\_TELNET\_PORT**

This property specifies the port number of the port that is used for connections to the Apache Felix Remote Shell (<http://felix.apache.org/site/apache-felix-remote-shell.html>). This shell uses the Felix shell service to interact with the OSGi module management subsystem. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

# Operands

## source-configuration-name

The name of the configuration that you are copying.

## destination-configuration-name

The name of the configuration that you are creating by copying the source configuration.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period
  - Underscore
- The name must be unique in the domain and must not be the name of another named configuration, a cluster, a Eclipse GlassFish instance , or a node.
- The name must not be `domain`, `server`, or any other keyword that is reserved by Eclipse GlassFish.

# Examples

## Example 1 Copying a Configuration

This example copies the `default-config` configuration to the `pmdsaconfig` configuration, overriding the settings for the following ports:

- HTTP listener port
- HTTPS listener port

```
asadmin> copy-config  
--systemproperties HTTP_LISTENER_PORT=2000:HTTP_SSL_LISTENER_PORT=3000  
default-config pmdsaconfig
```

Command copy-config executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[delete-config\(1\)](#), [list-configs\(1\)](#)

# create-admin-object

Adds the administered object with the specified JNDI name for a resource adapter

## Synopsis

```
asadmin [asadmin-options] create-admin-object [--help]
[--target target]
--restype restype
[--classname classname]
--rname rname
[--enabled={true|false}]
[--description description]
[--property name=value[:name=value]*]
jndi_name
```

## Description

The **create-admin-object** subcommand creates the administered object with the specified JNDI name and the interface definition for a resource adapter.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target on which you are creating the administered object. Valid values are as follows:

##### **server**

Creates the administered object for the default server instance **server** and is the default value.

##### **configuration\_name**

Creates the administered object for the named configuration.

**cluster\_name**

Creates the administered object for every server instance in the cluster.

**instance\_name**

Creates the administered object for a particular server instance.



The resource is always created for the domain as a whole, but the [resource-ref](#) for the resource is only created for the specified [--target](#). This means that although the resource is defined at the domain level, it is only available at the specified target level. Use the [create-resource-ref](#) subcommand to refer to the resource in multiple targets if needed.

**--restype**

Specifies the interface definition for the administered object. The resource type must be an interface definition that is specified in the [ra.xml](#) file of the resource adapter.

**--classname**

Specifies the class name of the administered object. Required if multiple administered objects use the same interface definition.

**--raname**

Specifies the name of the resource adapter associated with this administered object.

**--enabled**

Specifies if this object is enabled. Default is true.

**--description**

Text string describing the administered object.

**--property**

Description of the name/values pairs for configuring the resource. Dependent on the resource adapter. For JMS properties, see [create-jms-resource\(1\)](#) for JMS destination resources.

## Operands

**jndi\_name**

JNDI name of the administered object to be created.

## Examples

## Example 1 Creating an Administered Object

In this example, `jmsra` is a system resource adapter with the admin object interfaces, `jakarta.jms.Queue` and `jakarta.jms.Topic`.

```
asadmin> create-admin-object --restype jakarta.jms.Queue  
--rname jmsra --description "sample administered object"  
--property Name=sample_jmsqueue jms/samplequeue  
Command create-admin-object executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-resource-ref\(1\)](#), [delete-admin-object\(1\)](#), [list-admin-objects\(1\)](#)

# create-application-ref

Creates a reference to an application

## Synopsis

```
asadmin [asadmin-options] create-application-ref [--help]
[--target target]
[--virtualservers virtual_servers] [--enabled=true]
[--lbenabled=true] reference_name
```

## Description

The `create-application-ref` subcommand creates a reference from a cluster or an unclustered server instance to a previously deployed application element (for example, a Jakarta EE application, a Web module, or an enterprise bean module). This effectively results in the application element being deployed and made available on the targeted instance or cluster.

The target instance or instances making up the cluster need not be running or available for this subcommand to succeed. If one or more instances are not available, they will receive the new application element the next time they start.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target for which you are creating the application reference. Valid values are

- `server`- Specifies the default server instance as the target for creating the application reference. `server` is the name of the default server instance and is the default value for this option.
- `cluster_name`- Specifies a particular cluster as the target for creating the application reference.
- `instance_name`- Specifies a particular stand-alone server instance as the target for creating the application reference.

**--virtualservers**

Specifies a comma-separated list of virtual server IDs on which to deploy. This option applies only to Web modules (either standalone or in a Jakarta EE application). If this option is not specified, the application is deployed to all virtual servers except the administrative server, [\\_asadmin](#).

**--enabled**

Indicates whether the application should be enabled (that is, loaded). This value will take effect only if the application is enabled at the global level. The default is `true`.

**--lbenabled**

Controls whether the deployed application is available for load balancing. The default is true.

## Operands

**reference\_name**

The name of the application or module, which can be a Jakarta EE application, Web module, EJB module, connector module, application client module, or lifecycle module.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. If the **--enabled** option is set to false, you can create references to multiple disabled versions by using an asterisk (\*) as a wildcard character. For more information about module and application versions, see "[Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

## Examples

### Example 1 Creating an Application Reference

The following example creates a reference to the Web module `MyWebApp` on the unclustered server instance `NewServer`.

```
asadmin> create-application-ref --target NewServer MyWebApp
Command create-application-ref executed successfully.
```

## Exit Status

**0**

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[delete-application-ref\(1\)](#), [list-application-refs\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# create-audit-module

Adds an audit module

## Synopsis

```
asadmin [asadmin-options] create-audit-module [--help]
--classname classname
[--property(name=value)[:name=value]*]
[--target target]
audit_module_name
```

## Description

The **create-audit-module** subcommand adds the named audit module for the Java class that implements the audit capabilities. Audit modules collect and store information on incoming requests (from, for example, servlets and EJB components) and outgoing responses.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --classname

The name of the Java class that implements this audit module. If not specified, this option defaults to [com.sun.enterprise.security.Audit](#).

#### --help

#### -?

Displays the help text for the subcommand.

#### --property

Optional keyword-value pairs that specify additional properties for the audit module.

Audit module properties that are defined by Eclipse GlassFish are as follows:

#### **auditOn**

If **true**, specifies that the audit module is loaded and called by the Eclipse GlassFish audit library at audit points.

Other available properties are determined by the implementation of the audit module.

**--target**

Specifies the target on which you are creating the audit module. Valid values are as follows:

**server**

Creates the audit module for the default server instance **server** and is the default value.

**configuration\_name**

Creates the audit module for the named configuration.

**cluster\_name**

Creates the audit module for every server instance in the cluster.

**instance\_name**

Creates the audit module for a particular server instance.

## Operands

**audit\_module\_name**

The name of this audit module.

## Examples

### Example 1 Creating an audit module

```
asadmin> create-audit-module  
--classname com.sun.appserv.auditmodule  
--property defaultuser=admin:Password=admin sampleAuditModule  
Command create-audit-module executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

---

[delete-audit-module\(1\)](#), [list-audit-modules\(1\)](#)

# create-auth-realm

Adds the named authentication realm

## Synopsis

```
asadmin [asadmin-options] create-auth-realm [--help]
--classname realm_class [--property(name=value)[:name=value]*]
[--target target_name] auth_realm_name
```

## Description

The **create-auth-realm** subcommand adds the named authentication realm.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target on which you are creating the realm. Valid values are

##### server

Creates the realm on the default server instance. This is the default value.

##### configuration\_name

Creates the realm in the specified configuration.

##### cluster\_name

Creates the realm on all server instances in the specified cluster.

##### instance\_name

Creates the realm on a specified server instance.

#### --classname

Java class which implements this realm. These include

`com.sun.enterprise.security.auth.realm.FileRealm`,  
`com.sun.enterprise.security.auth.realm.certificate.CertificateRealm`,  
`com.sun.enterprise.security.auth.realm.jdbc.JDBCRealm`,  
`com.sun.enterprise.security.auth.realm.ldap.LDAPRealm`,  
`com.sun.enterprise.security.auth.realm.ldap.PamRealm`,  
`com.sun.enterprise.security.auth.realm.solaris.SolarisRealm`, or a custom realm.

and

#### --property

Optional attribute name-value pairs for configuring the authentication realm. Authentication realms require provider-specific properties, which vary based on implementation.

The following properties are common to all of the supported realms, which include `FileRealm`, `CertificateRealm`, `JDBCRealm`, `LDAPRealm`, `PamRealm`, and `SolarisRealm`.

#### jaas-context

Specifies the Java Authentication and Authorization Service (JAAS) context.

#### assign-groups

(Optional) If this property is set, its value is taken to be a comma-separated list of group names. All clients who present valid certificates are assigned membership to these groups for the purposes of authorization decisions in the web and EJB containers.

Specific to each realm, you can specify the following properties.

- You can specify the following properties for `FileRealm`:

#### file

Specifies the file that stores user names, passwords, and group names. The default is domain-dir/`config/keyfile`.

- You can specify the following properties for `CertificateRealm`:

#### LoginModule

Specifies the name of a JAAS `LoginModule` to use for performing authentication. To use a JAAS `LoginModule`, you must first create an implementation of the `javax.security.auth.spi.LoginModule` interface, and then plug the module into a `jaas-context`. For more information, see "[Custom Authentication of Client Certificate in SSL Mutual Authentication](#)" in Eclipse GlassFish Security Guide.

- You can specify the following properties for `JDBCRealm`:

#### datasource-jndi

Specifies the `jndi-name` of the `jdbc-resource` for the database.

#### user-table

Specifies the name of the user table in the database.

**user-name-column**

Specifies the name of the user name column in the database's user table.

**password-column**

Specifies the name of the password column in the database's user table.

**group-table**

Specifies the name of the group table in the database.

**group-table**

Specify the group table for an authentication realm of class [JDBCRealm](#).

**group-name-column**

Specifies the name of the group name column in the database's group table.

**db-user**

(Optional) Allows you to specify the database user name in the realm instead of the [jdbc-connection-pool](#). This prevents other applications from looking up the database, getting a connection, and browsing the user table. By default, the [jdbc-connection-pool](#) configuration is used.

**db-password**

(Optional) Allows you to specify the database password in the realm instead of the [jdbc-connection-pool](#). This prevents other applications from looking up the database, getting a connection, and browsing the user table. By default, the [jdbc-connection-pool](#) configuration is used.

**group-table**

Specifies the name of the group table in the database.

**digest-algorithm**

(Optional) Specifies the digest algorithm. The default is [SHA-256](#). You can use any algorithm supported in the JDK, or none.

In versions of Eclipse GlassFish prior to 5.0, the default algorithm was [MD5](#). If you have applications that depend on the [MD5](#) algorithm, you can override the default [SHA-25](#) algorithm by using the [asadmin set](#) subcommand:

```
asadmin> set server.security-service.property.default-digest-algorithm=MD5
```



You can use the [asadmin get](#) subcommand to determine what algorithm is currently being used:

```
asadmin> get server.security-service.property.default-digest-algorithm
```

Also note that, to maintain backward compatibility, if an upgrade is performed from Eclipse GlassFish v2.x or v3.0.x to Eclipse GlassFish 5.0, the default algorithm is automatically set to [MD5](#) in cases where the digest algorithm had not been explicitly set in the older Eclipse GlassFish version.

#### **digestrealm-password-enc-algorithm**

(Optional) Specifies the algorithm for encrypting passwords stored in the database.



It is a security risk not to specify a password encryption algorithm.

#### **encoding**

(Optional) Specifies the encoding. Allowed values are [Hex](#) and [Base64](#). If [digest-algorithm](#) is specified, the default is [Hex](#). If [digest-algorithm](#) is not specified, by default no encoding is specified.

#### **charset**

(Optional) Specifies the [charset](#) for the digest algorithm.

- You can specify the following properties for [LDAPRealm](#):

#### **directory**

Specifies the LDAP URL to your server.

#### **base-dn**

Specifies the LDAP base DN for the location of user data. This base DN can be at any level above the user data, since a tree scope search is performed. The smaller the search tree, the better the performance.

#### **search-filter**

(Optional) Specifies the search filter to use to find the user. The default is [uid=%s](#) ([%s](#) expands

to the subject name).

#### group-base-dn

(Optional) Specifies the base DN for the location of groups data. By default, it is same as the **base-dn**, but it can be tuned, if necessary.

#### group-search-filter

(Optional) Specifies the search filter to find group memberships for the user. The default is **uniqueMember=%d** (%d expands to the user **elementDN**).

#### group-target

(Optional) Specifies the LDAP attribute name that contains group name entries. The default is **CN**.

#### search-bind-dn

(Optional) Specifies an optional DN used to authenticate to the directory for performing the search-filter lookup. Only required for directories that do not allow anonymous search.

#### search-bind-password

(Optional) Specifies the LDAP password for the DN given in **search-bind-dn**.

## Operands

### auth\_realm\_name

A short name for the realm. This name is used to refer to the realm from, for example, [web.xml](#).

## Examples

### Example 1 Creating a New Authentication Realm

This example creates a new file realm.

```
asadmin> create-auth-realm  
--classname com.sun.enterprise.security.auth.realm.file.FileRealm  
--property file=${com.sun.aas.instanceRoot}/config/  
admin-keyfile:jaas-context=fileRealm file  
Command create-auth-realm executed successfully
```

Where **file** is the authentication realm created.

---

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-auth-realm\(1\)](#), [list-auth-realms\(1\)](#)

# create-cluster

Creates a Eclipse GlassFish cluster

## Synopsis

```
asadmin [asadmin-options] create-cluster [--help]
[--config config-name]
[--systemproperties (name=value)[:name=value]*]
[--properties (name=value)[:name=value]*]
[--gmsenabled={true|false}]
[--multicastport multicast-port]
[--multicastaddress multicast-address]
[--bindaddress bind-address]
[--hosts hadb-host-list]
[--haagentport port-number]
[--haadminpassword password]
[--haadminpasswordfile file-name] [--devicesize devicesize ]
[--haproperty (name=value)[:name=value]*]
[--autohadb=false] [--portbase port-number]
cluster-name
```

## Description

The `create-cluster` subcommand creates a Eclipse GlassFish cluster. Initially the cluster contains no Eclipse GlassFish instances, applications, or resources.

A cluster requires a reference to the named configuration that defines the configuration of all instances that are added to the cluster. The configuration can be specified in the command to create the cluster, but is not required. If no configuration is specified, the subcommand creates a configuration that is named `cluster-name`-config`` for the cluster. The cluster that is created is a standalone cluster because the cluster's configuration is not shared with any other clusters or standalone instances.

To add instances to the cluster, set the `--cluster` option to the name of the cluster when using either of the following subcommands:

- [create-instance\(1\)](#)
- [create-local-instance\(1\)](#)

To delete server instances from the cluster at any time, use one of the following subcommands:

- [delete-instance\(1\)](#)

- [delete-local-instance\(1\)](#)

To associate applications and resources with all instances in the cluster, set the `--target` option to the name of the cluster when performing the following operations:

- Deploying applications by using the [deploy\(1\)](#) subcommand
- Creating resources by using subcommands such as [create-jdbc-resource\(1\)](#)
- Creating references to applications that are already deployed in other targets by using the [create-application-ref\(1\)](#) subcommand
- Creating references to resources that are already created in other targets by using the [create-resource-ref\(1\)](#) subcommand

This subcommand is supported in remote mode only.

## Options

### **asadmin-options**

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--config**

Specifies the named configuration that the cluster references. The configuration must exist and must not be named `default-config` or `server-config`. Specifying the `--config` option creates a shared cluster. If this option is omitted, a standalone cluster is created.

**--systemproperties**

Defines system properties for the configuration that is created for the cluster. These properties override the property values in the `default-config` configuration. The following properties are available:

#### **ASADMIN\_LISTENER\_PORT**

This property specifies the port number of the HTTP port or HTTPS port through which the DAS connects to the instance to manage the instance. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

#### **HTTP\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTP requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**HTTP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTPS requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**IIOP\_LISTENER\_PORT**

This property specifies the port number of the port that is used for IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**IIOP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**IIOP\_SSL\_MUTUALAUTH\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections with client authentication. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**JAVA\_DEBUGGER\_PORT**

This property specifies the port number of the port that is used for connections to the [Java Platform Debugger Architecture \(JPDA\)](http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugger. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**JMS\_PROVIDER\_PORT**

This property specifies the port number for the Java Message Service provider. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**JMX\_SYSTEM\_CONNECTOR\_PORT**

This property specifies the port number on which the JMX connector listens. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**OSGI\_SHELL\_TELNET\_PORT**

This property specifies the port number of the port that is used for connections to the [Apache Felix Remote Shell](http://felix.apache.org/site/apache-felix-remote-shell.html) (<http://felix.apache.org/site/apache-felix-remote-shell.html>). This shell uses the Felix shell service to interact with the OSGi module management subsystem. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**--properties**

Defines properties for the cluster. The following properties are available:

**GMS\_DISCOVERY\_URI\_LIST**

The locations of Eclipse GlassFish instances in the cluster to use for discovering the cluster. This property is required only if the Group Management Service (GMS) is not using multicast for

broadcasting messages.

Valid values for this property are as follows:

- A comma-separated list of uniform resource identifiers (URIs). Each URI must locate a Eclipse GlassFish instance or the DAS. This format is required if multiple Eclipse GlassFish instances are running on the same host.  
The format of each URI in the list is as follows:  
`scheme://host-name-or -IP-address:port`
  - scheme is the URI scheme, which is `tcp`.
  - host-name-or -IP-address is the host name or IP address of the host on which the instance is running.
  - port is the port number of the port on which the instance listens for messages from GMS. The system property `GMS_LISTENER_PORT`-clustername must be set for the instance. For information about how to set this system property for an instance, see "[Discovering a Cluster When Multicast Transport Is Unavailable](#)" in Eclipse GlassFish High Availability Administration Guide.
- A comma-separated list of IP addresses or host names on which the DAS or the instances are running. The list can contain a mixture of IP addresses and host names. This format can be used only if one clustered instance is running on each host. The value of the `GMS_LISTENER_PORT` property must be unique for each cluster in a domain.
- The keyword `generate`. This format can be used only if one instance in a cluster is running on each host and the DAS is running on a separate host. Multiple instances on the same host cannot be members of the same cluster. The value of the `GMS_LISTENER_PORT` property must be unique for each cluster in a domain.

#### **`GMS_LISTENER_PORT`**

The port number of the port on which the cluster listens for messages from GMS.

The default value is a reference to the `GMS_LISTENER_PORT`-cluster-name system property. By default, this system property is not set. In this situation, GMS selects a free port from the range that is defined by the properties `GMS_TCPISTARPORT` and `GMS_TCPEndPort`. By default, this range is 9090-9200. In most situations, the default behavior should suffice.

However, if GMS is not using multicast for broadcasting messages, the `GMS_LISTENER_PORT` property must specify a port number that is valid for all Eclipse GlassFish instances in the cluster. To use the default value to meet this requirement, use a system property to set the port number individually for each instance.

For example, use the `create-system-properties` subcommand to create the system property `GMS_LISTENER_PORT`-cluster-name for the DAS. Then, for each instance in the cluster, set the `GMS_LISTENER_PORT`-cluster-name system property to the port number on which the instance listens for messages from GMS. The default value of the `GMS_LISTENER_PORT` property for the cluster references this system property.

#### **`GMS_LOOPBACK`**

Specifies whether an instance may receive from itself application-level messages that the

instance broadcasts to the cluster. Possible values are as follows:

- **false** The instance may not receive messages from itself (default).
- **true** The instance may receive messages from itself. Use this setting for testing an instance when the instance is the only instance in a cluster.

#### GMS\_MULTICAST\_TIME\_TO\_LIVE

The maximum number of iterations or transmissions that a multicast message for the following types of events can experience before the message is discarded:

- Group discovery
- Member heartbeats
- Membership changes

To match the configuration of the network on which the DAS and clustered instances are deployed, set this value as low as possible. To determine the lowest possible value for your system, use the [validate-multicast\(1\)](#) subcommand.

- A value of 0 ensures that multicast messages never leave the host from which they are broadcast.
- A value of 1 might prevent the broadcast of messages between hosts on same subnet that are connected by a switch or a router.
- The default is 4, which ensures that messages are successfully broadcast to all cluster members in networks where hosts are connected by switches or routers.

#### GMS\_TCPEndPort

The highest port number in the range from which GMS selects a free port if the **GMS\_LISTENER\_PORT**-cluster-name system property is not set. The default is 9200.

#### GMS\_TCPEndPort

The lowest port number in the range from which GMS selects a free port if the **GMS\_LISTENER\_PORT**-cluster-name system property is not set. The default is 9090.

#### --gmseabled

Specifies whether GMS is enabled for the cluster. Possible values are as follows:

##### true

GMS is enabled for the cluster (default). When GMS is enabled for a cluster, GMS is started in each server instance in the cluster and in the DAS. The DAS participates in each cluster for which this option is set to **true**.

##### false

GMS is disabled for the cluster.

### --multicastaddress

The address on which GMS listens for group events. This option must specify a multicast address in the range 224.0.0.0 through 239.255.255.255. The default is 228.9.XX.YY, where XX and YY are automatically generated independent values between 0 and 255.

### --multicastport

The port number of communication port on which GMS listens for group events. This option must specify a valid port number in the range 2048-49151. The default is an automatically generated value in this range.

### --bindaddress

The Internet Protocol (IP) address of the network interface to which GMS binds. This option must specify the IP address of a local network interface. The default is all public network interface addresses.

On a multihome machine, this option configures the network interface that is used for the GMS. A multihome machine possesses two or more network interfaces.

To specify an address that is valid for all Eclipse GlassFish instances in the cluster, use a system property to set the address individually for each instance.

For example, use the `create-system-properties` subcommand to create the system property `GMS-BIND-INTERFACE-ADDRESS-cluster-name`. Then set the `--bindaddress` option of this subcommand to ``${GMS-BIND-INTERFACE-ADDRESS-cluster-name}`` to specify the system property. Finally, for each instance in the cluster, set the `GMS-BIND-INTERFACE-ADDRESS-cluster-name` system property to the required network interface address on the instance's machine.

### --hosts

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

### --haagentport

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

### --haadminpassword

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

### --haadminpasswordfile

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--devicesize**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--haproperty**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--autohadb**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--portbase**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

# Operands

**cluster-name**

The name of the cluster.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period
  - Underscore
- The name must be unique in the domain and must not be the name of another cluster, a named configuration, a Eclipse GlassFish instance, or a node.
- The name must not be **domain**, **server**, or any other keyword that is reserved by Eclipse GlassFish. If the **configure-jms-cluster(1)** subcommand is to be used to configure a Message Queue cluster to provide JMS services to the Eclipse GlassFish cluster, the length of the Eclipse GlassFish

cluster name is might be restricted:

- If `clustertype` is set to `enhanced` in the `configure-jms-cluster(1)` subcommand, the name can be no longer than  $n-21$  characters, where  $n$  is the maximum table name length allowed by the database.
- If `configstoretype` is set to `shareddb` in the `configure-jms-cluster(1)` subcommand, the name can be no longer than  $n-19$  characters, where  $n$  is the maximum table name length allowed by the database.

## Examples

### Example 1 Creating a Cluster

This example creates a cluster that is named `ltscluster` for which port 1169 is to be used for secure IIOP connections. Because the `--config` option is not specified, the cluster references a copy of the named configuration `default-config` that is named `ltscluster-config`.

```
asadmin> create-cluster
--systemproperties IIOP_SSL_LISTENER_PORT=1169
ltscluster
Command create-cluster executed successfully.
```

### Example 2 Creating a Cluster With a List of URIs for Discovering the Cluster

This example creates a cluster that is named `tcpcluster`. In this example, GMS is not using multicast for broadcasting messages and multiple instances reside on the same host. Therefore, the `GMS_DISCOVERY_URI_LIST` property is set to the locations of the Eclipse GlassFish instances to use for discovering the cluster. These instances reside on the host whose IP address is `10.152.23.224` and listen for GMS events on ports 9090, 9091, and 9092.

To distinguish colon (:) characters in URIs from separators in a property list, colons in URIs are escaped with single quote characters ('') and backslash (\) characters. For more information about escape characters in options for the `asadmin` utility, see the `asadmin(1M)` help page.

This example assumes that the port on which each instance listens for GMS messages is set independently for the instance through the `GMS_LISTENER_PORT-tcpcluster` system property. For information about how to set the port on which an instance listens for GMS messages, see "Discovering a Cluster When Multicast Transport Is Unavailable" in Eclipse GlassFish High Availability Administration Guide.

```
asadmin> create-cluster --properties GMS_DISCOVERY_URI_LIST=
tcp'\\:'//10.152.23.224'\\:'9090,
tcp'\\:'//10.152.23.224'\\:'9091,
tcp'\\:'//10.152.23.224'\\:'9092 tcpcluster
Command create-cluster executed successfully.
```

## Example 3 Creating a Cluster With a List of IP Addresses for Discovering the Cluster

This example creates a cluster that is named `ipcluster`. In this example, GMS is not using multicast for broadcasting messages and only one clustered instance resides on each host. Therefore, the `GMS_DISCOVERY_URI_LIST` property is set to the IP addresses of the hosts where instances to use for discovering the cluster are running. The cluster listens for messages from GMS on port 9090.

```
asadmin> create-cluster --properties 'GMS_DISCOVERY_URI_LIST=
10.152.23.225,10.152.23.226,10.152.23.227,10.152.23.228:
GMS_LISTENER_PORT=9090' ipcluster
Command create-cluster executed successfully.
```

## Example 4 Creating a Cluster With a Generated List of Instances for Discovering the Cluster

This example creates a cluster that is named `gencluster`. In this example, GMS is not using multicast for broadcasting messages, one instance in the cluster is running on each host and the DAS is running on a separate host. Therefore, the `GMS_DISCOVERY_URI_LIST` property is set to the keyword `generate` to generate a list of instances to use for discovering the cluster. The cluster listens for messages from GMS on port 9090.

```
asadmin> create-cluster --properties 'GMS_DISCOVERY_URI_LIST=generate:
GMS_LISTENER_PORT=9090' gencluster
Command create-cluster executed successfully.
```

## Exit Status

0

command executed successfully

---

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-application-ref\(1\)](#), [create-instance\(1\)](#), [create-jdbc-resource\(1\)](#), [create-local-instance\(1\)](#), [create-resource-ref\(1\)](#), [delete-cluster\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [deploy\(1\)](#), [list-clusters\(1\)](#), [start-cluster\(1\)](#), [stop-cluster\(1\)](#), [validate-multicast\(1\)](#)

"[Discovering a Cluster When Multicast Transport Is Unavailable](#)" in Eclipse GlassFish High Availability Administration Guide

Apache Felix Remote Shell (<http://felix.apache.org/site/apache-felix-remote-shell.html>), Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# create-connector-connection-pool

Adds a connection pool with the specified connection pool name

## Synopsis

```
asadmin [asadmin-options] create-connector-connection-pool [--help]
[--target=target]
[--raname raname]
--connectiondefinition connectiondefinitionname
[--steadypoolsize steadypoolsize]
[--maxpoolsize maxpoolsize]
[--maxwait maxwait]
[--poolresize poolresize]
[--idletimeout idletimeout]
[--isconnectvalidatereq={false|true}]
[--failconnection={false|true}]
[--leaktimeout=timeout]
[--leakreclaim={false|true}]
[--creationretryattempts=attempts]
[--creationretryinterval=interval]
[--lazyconnectionenlistment={false|true}]
[--lazyconnectionassociation={false|true}]
[--associatewiththread={false|true}]
[--matchconnections={true|false}]
[--maxconnectionusagecount=count]
[--validateatmostonceperiod=interval]
[--transactionsupport transactionsupport]
[--descrip[tion description]
[--ping {false|true}]
[--pooling {true|false}]
[--property (name=value)[:name=value]*]
poolname
```

## Description

The `create-connector-connection-pool` subcommand defines a pool of connections to an enterprise information system (EIS). The named pool can be referred to by multiple connector resources. Each defined pool is instantiated at server startup, and is populated when accessed for the first time. If two or more connector resources point to the same connector connection pool, they are using the same pool of connections at run time. There can be more than one pool for a connection definition in a single resource adapter.

A connector connection pool with authentication can be created either by using a `--property` option to

specify user, password, or other connection information, or by specifying the connection information in the XML descriptor file.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --associatewiththread

Specifies whether a connection is associated with the thread to enable the thread to reuse the connection. If a connection is not associated with the thread, the thread must obtain a connection from the pool each time that the thread requires a connection. Possible values are as follows:

##### false

A connection is not associated with the thread (default).

##### true

A connection is associated with the thread.

#### --connectiondefinition

The name of the connection definition.

#### --creationretryattempts

Specifies the maximum number of times that the server retries to create a connection if the initial attempt fails.

Default value is 0, which specifies that the server does not retry to create the connection.

#### --creationretryinterval

Specifies the interval, in seconds, between successive attempts to create a connection.

If `--creationretryattempts` is 0, the `--creationretryinterval` option is ignored. Default value is 10.

#### --description

Text providing descriptive details about the connector connection pool.

#### --failconnection

If set to true, all connections in the pool are closed if a single validation check fails. This parameter is mandatory if the `--isconnectvalidatereq` option is set to true. Default value is false.

**--idletimeout**

The maximum time that a connection can remain idle in the pool. After this amount of time, the pool can close this connection. Default value is 300.

**--isconnectvalidatereq**

If the value is set to true, the connections will be checked to see if they are usable, before they are given out to the application. Default value is false.

**--lazyconnectionenlistment**

Specifies whether a resource to a transaction is enlisted only when a method actually uses the resource. Default value is false.

**--lazyconnectionassociation**

Specifies whether a physical connection should be associated with the logical connection only when the physical connection is used, and disassociated when the transaction is completed. Such association and dissociation enable the reuse of physical connections. Possible values are as follows:

**false**

A physical connection is associated with the logical connection even before the physical connection is used, and is not disassociated when the transaction is completed (default).

**true**

A physical connection is associated with the logical connection only when the physical connection is used, and disassociated when the transaction is completed. The **--lazyconnectionenlistment** option must also be set to **true**.

**--leakreclaim**

Specifies whether leaked connections are restored to the connection pool after leak connection tracing is complete. Possible values are as follows:

**false**

Leaked connections are not restored to the connection pool (default).

**true**

Leaked connections are restored to the connection pool.

**--leaktimeout**

Specifies the amount of time, in seconds, for which connection leaks in a connection pool are to be traced.

If connection leak tracing is enabled, you can use the Administration Console to enable monitoring of the JDBC connection pool to get statistics on the number of connection leaks. Default value is 0, which disables connection leak tracing.

**--matchconnections**

Specifies whether a connection that is selected from the pool should be matched with the resource

adaptor. If all connections in the pool are identical, matching between connections and resource adapters is not required. Possible values are as follows:

**true**

A connection should be matched with the resource adaptor (default).

**false**

A connection should not be matched with the resource adaptor.

**--maxconnectionusagecount**

Specifies the maximum number of times that a connection can be reused.

When this limit is reached, the connection is closed. Default value is 0, which specifies no limit on the number of times that a connection can be reused.

**--maxpoolsize**

The maximum number of connections that can be created to satisfy client requests. Default value is 32.

**--maxwait**

The amount of time, in milliseconds, that a caller must wait before a connection is created, if a connection is not available. If set to 0, the caller is blocked indefinitely until a resource is available or until an error occurs. Default value is 60000.

**--ping**

A pool with this attribute set to true is contacted during creation (or reconfiguration) to identify and warn of any erroneous values for its attributes. Default value is false.

**--pooling**

When set to false, this attribute disables connection pooling. Default value is true.

**--poolresize**

Quantity by which the pool will scale up or scale down the number of connections. Scale up: When the pool has no free connections, pool will scale up by this quantity. Scale down: All the invalid and idle connections are removed, sometimes resulting in removing connections of quantity greater than this value. The number of connections that is specified by **--steadypoolsize** will be ensured. Possible values are from 0 to **MAX\_INTEGER**. Default value is 2.

**--property**

Optional attribute name/value pairs for configuring the pool.

**LazyConnectionEnlistment**

Deprecated. Use the equivalent option. Default value is false.

**LazyConnectionAssociation**

Deprecated. Use the equivalent option. Default value is false.

**AssociateWithThread**

Deprecated. Use the equivalent option. Default value is false.

**MatchConnections**

Deprecated. Use the equivalent option. Default value is false.

**--rname**

The name of the resource adapter.

**--steadyPoolSize**

The minimum and initial number of connections maintained in the pool. Default value is 8.

**--target**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--transactionSupport**

Indicates the level of transaction support that this pool will have. Possible values are **XATransaction**, **LocalTransaction** and **NoTransaction**. This attribute can have a value lower than or equal to but not higher than the resource adapter's transaction support attribute. The resource adapter's transaction support attribute has an order of values, where **XATransaction** is the highest, and **NoTransaction** the lowest.

**--validateAtMostOncePeriod**

Specifies the time interval in seconds between successive requests to validate a connection at most once. Setting this attribute to an appropriate value minimizes the number of validation requests by a connection. Default value is 0, which means that the attribute is not enabled.

## Operands

**poolname**

The name of the connection pool to be created.

## Examples

### Example 1 Creating a Connector Connection Pool

This example creates a new connector connection pool named **jms/qConnPool**.

```
asadmin> create-connector-connection-pool --raname jmsra  
--connectiondefinition jakarta.jms.QueueConnectionFactory --steadypoolsize 20  
--maxpoolsize 100 --poolresize 2 --maxwait 60000 jms/qConnPool  
Command create-connector-connection-pool executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-connector-connection-pool\(1\)](#), [list-connector-connection-pools\(1\)](#), [ping-connection-pool\(1\)](#)

# create-connector-resource

Registers the connector resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] create-connector-resource [--help]
--poolname connectorConnectionPoolName
[--enabled={true|false}]
[--description description]
[--objecttype objecttype]
[--property (name=value)[:name=value]*]
[--target target]
jndi_name
```

## Description

The `create-connector-resource` subcommand registers the connector resource with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --poolname

The name of the connection pool. When two or more resource elements point to the same connection pool element, they use the same pool connections at runtime.

#### --enabled

This option determines whether the resource is enabled at runtime. The default value is true.

#### --objecttype

Defines the type of the connector resource. Default is user. Allowed values are:

**system-all**

A system resource for all server instances and the domain administration server (DAS).

**system-admin**

A system resource only for the DAS.

**system-instance**

A system resource for all server instances only.

**user**

A user resource.

**--description**

Text providing details about the connector resource.

**--property**

Optional attribute name value pairs for configuring the resource.

**--target**

This option specifies the ending location of the connector resources. Valid targets are:

**server**

Creates the connector resource in the default server instance. This is the default value.

**domain**

Creates the connector resource in the domain.

**cluster\_name**

Creates the connector resource in every server instance in the cluster.

**instance\_name**

Creates the connector resource in the specified server instance.



The resource is always created for the domain as a whole, but the **resource-ref** for the resource is only created for the specified **--target**. This means that although the resource is defined at the domain level, it is only available at the specified target level. Use the **create-resource-ref** subcommand to refer to the resource in multiple targets if needed.

# Operands

**jndi\_name**

The JNDI name of this connector resource.

# Examples

## Example 1 Creating a Connector Resource

This example creates a connector resource named `jms/qConnFactory`.

```
asadmin> create-connector-resource --poolname jms/qConnPool  
--description "sample connector resource" jms/qConnFactory  
Command create-connector-resource executed successfully
```

## Example 2 Using the create-connector-resource subcommand

This example shows the usage of this subcommand.

```
asadmin> create-connector-resource --target server --poolname jms/qConnPool  
--description "sample connector resource" jms/qConnFactory  
Command create-connector-resource executed successfully
```

Where `jms/qConnFactory` is the sample connector resource that is created.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-connector-resource\(1\)](#), [list-connector-resources\(1\)](#), [create-resource-ref\(1\)](#)

# create-connector-security-map

Creates a security map for the specified connector connection pool

## Synopsis

```
asadmin [asadmin-options] create-connector-security-map [--help]
--poolname connector_connection_pool_name
[--principals principal-name1[,principal-name2]*]
[--usergroups user-group1[,user-group2]*]
[--mappedusername user-name]
[--target target]
mapname
```

## Description

The `create-connector-security-map` subcommand creates a security map for the specified connector connection pool. If the security map is not present, a new one is created. This subcommand can also map the caller identity of the application (principal or user group) to a suitable enterprise information system (EIS) principal in container-managed authentication scenarios. The EIS is any system that holds the data of an organization. It can be a mainframe, a messaging system, a database system, or an application. One or more named security maps can be associated with a connector connection pool. The connector security map configuration supports the use of the wild card asterisk (\*) to indicate all users or all user groups.

To specify the EIS password, you can add the `AS_ADMIN_MAPPEDPASSWORD` entry to the password file, then specify the file by using the `--passwordfile asadmin` utility option.

For this subcommand to succeed, you must have first created a connector connection pool using the `create-connector-connection-pool` subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--poolname**

Specifies the name of the connector connection pool to which the security map belongs.

**--principals**

Specifies a list of backend EIS principals. More than one principal can be specified using a comma-separated list. Use either the **--principals** or **--usergroups** options, but not both in the same command.

**--usergroups**

Specifies a list of backend EIS user group. More than one user groups can be specified using a comma separated list. Use either the **--principals** or **--usergroups** options, but not both in the same command.

**--mappedusername**

Specifies the EIS username.

**--target**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

**mapname**

The name of the security map to be created.

## Examples

### Example 1 Creating a Connector Security Map

This example creates **securityMap1** for the existing connection pool named **connector-pool1**.

```
asadmin> create-connector-security-map --poolname connector-pool1  
--principals principal1,principal2 --mappedusername backend-username securityMap1  
Command create-connector-security-map executed successfully
```

## Exit Status

0

subcommand executed successfully

---

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-connector-security-map\(1\)](#), [list-connector-security-maps\(1\)](#), [update-connector-security-map\(1\)](#)

# create-connector-work-security-map

Creates a work security map for the specified resource adapter

## Synopsis

```
asadmin [asadmin-options] create-connector-work-security-map [--help]
--rname rname
[--principalsmap eis-principal1=principal_name1[, eis-principal2=principal_name2]*]
[--groupsmap eis-group1=server-group1[, eis-group2=server-group2]*}
[--description description]
mapname
```

## Description

The **create-connector-work-security-map** subcommand maps the caller identity of the work submitted by the resource adapter EIS principal or EIS user group to a suitable principal or user group in the Eclipse GlassFish security domain. One or more work security maps may be associated with a resource adapter. The connector work security map configuration supports the use of the wild card asterisk (\*) to indicate all users or all user groups.

The enterprise information system (EIS) is any system that holds the data of an organization. It can be a mainframe, a messaging system, a database system, or an application.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --description

Text providing descriptive details about the connector work security map.

#### --groupsmap

Specifies a map of the backend EIS user group to the Eclipse GlassFish user group. Use a comma-separated list to specify more than one mapping. Use either the **--principalsmap** option or the **--groupsmap** option, but not both.

### --principalsmap

Specifies a map of the backend EIS principal to the Eclipse GlassFish principal. Use a comma-separated list to specify more than one mapping. Use either the `--principalsmap` option or the `--groupsmap` option, but not both.

### --rname

Indicates the connector module name, which is the name of the resource adapter.

## Operands

### mapname

The name of the work security map to be created.

## Examples

### Example 1 Creating a Connector Work Security Map (Principal)

This example creates connector work security map `workSecurityMap1` that maps the backend EIS principal to the Eclipse GlassFish principal.

```
asadmin create-connector-work-security-map --rname my-resource-adapter  
--principalsmap eis-principal-1=server-principal-1,eis-principal-2  
=server-principal-2,eis-principal-3=server-principal-1  
workSecurityMap1  
Command create-connector-work-security-map executed successfully.
```

### Example 2 Creating a Connector Work Security Map (Group)

This example creates connector work security map `workSecurityMap2` that maps the backend EIS user group to the Eclipse GlassFish user group.

```
asadmin create-connector-work-security-map --rname my-resource-adapter  
--groupsmap eis-group-1=server-group-1,eis-group-2=server-group-2,  
eis-group-3=server-group-1 workSecurityMap2  
Command create-connector-work-security-map executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-connector-work-security-map\(1\)](#), [list-connector-work-security-maps\(1\)](#), [update-connector-work-security-map\(1\)](#)

# create-context-service

Creates a context service resource

## Synopsis

```
asadmin [asadmin-options] create-context-service [--help]
[--enabled={false|true}]
[--contextinfoenabled={false|true}]
[--contextinfo={Classloader|JNDI|Security|WorkArea}]
[--description description]
[--property property]
[--target target]
jndi_name
```

## Description

The **create-context-service** subcommand creates a context service resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --enabled

Determines whether the resource is enabled at runtime. The default value is **true**.

#### --contextinfoenabled

Determines whether container contexts are propagated to threads. If set to **true**, the contexts specified in the **--contextinfo** option are propagated. If set to **false**, no contexts are propagated and the **--contextinfo** option is ignored. The default value is **true**.

#### --contextinfo

Specifies individual container contexts to propagate to threads. Valid values are Classloader, JNDI, Security, and WorkArea. Values are specified in a comma-separated list and are case-insensitive. All contexts are propagated by default.

**--description**

Descriptive details about the resource.

**--property**

Optional attribute name/value pairs for configuring the resource.

Eclipse GlassFish does not define any additional properties for this resource. Moreover, this resource does not currently use any additional properties.

**--target**

Specifies the target for which you are creating the resource. Valid targets are:

**server**

Creates the resource for the default server instance. This is the default value.

**domain**

Creates the resource for the domain.

**cluster\_name**

Creates the resource for every server instance in the specified cluster.

**instance\_name**

Creates the resource for the specified server instance.

## Operands

**jndi\_name**

The JNDI name of this resource.

## Examples

### Example 1 Creating a Context Service Resource

This example creates a context service resource named `concurrent/myContextService`.

```
asadmin> create-context-service concurrent/myContextService
Context service concurrent/myContextService created successfully.
Command create-context-service executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-context-service\(1\)](#), [list-context-services\(1\)](#)

# create-custom-resource

Creates a custom resource

## Synopsis

```
asadmin [asadmin-options] create-custom-resource [--help]
--restype type --factoryclass classname
[--enabled={true|false}] [--description text]
[--property (name=value)[:name=value]*] jndi-name
[--target target]
```

## Description

The `create-custom-resource` subcommand creates a custom resource. A custom resource specifies a custom server-wide resource object factory that implements the `javax.naming.spi.ObjectFactory` interface.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

The target on which the custom resource you are creating will be available. Valid values are:

**server**

The resource will be available on the default server instance and all domains hosted on the instance. This is the default value.

**domain**

The resource will be available on the specified domain only.

**cluster\_name**

The resource will be available on every server instance in the cluster.

**instance\_name**

The resource will be available on the specified server instance only.



The resource is always created for the domain as a whole, but the **resource-ref** for the resource is only created for the specified **--target**. This means that although the resource is defined at the domain level, it is only available at the specified target level. Use the **create-resource-ref** subcommand to refer to the resource in multiple targets if needed.

**--restype**

The type of custom resource to be created. Specify a fully qualified type definition, for example `javax.naming.spi.ObjectFactory`. The resource type definition follows the format, `xxx`.xxx`.

**--factoryclass**

Factory class name for the custom resource. This class implements the `javax.naming.spi.ObjectFactory` interface.

**--enabled**

Determines whether the custom resource is enable at runtime. Default is true.

**--description**

Text providing details about the custom resource. This description is a string value and can include a maximum of 250 characters.

**--property**

Optional attribute name/value pairs for configuring the resource.

## Operands

**jndi-name**

The JNDI name of this resource.

## Examples

### Example 1 Creating a Custom Resource

This example creates a custom resource.

```
asadmin> create-custom-resource --restype topic
--factoryclass com.imq.topic mycustomresource
Command create-custom-resource executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-custom-resource\(1\)](#), [list-custom-resources\(1\)](#), [create-resource-ref\(1\)](#)

# create-domain

Creates a domain

## Synopsis

```
asadmin [asadmin-options] create-domain [--help]
[--adminport adminport]
[--instanceport instanceport]
[--portbase portbase]
[--profile profile-name]
[--template template-name]
[--domaindir domaindir]
[--savemasterpassword={false|true}]
[--usemasterpassword={false|true}]
[--domainproperties (name=value)[:name=value]*]
[--keytooloptions (name=value)[:name=value]*]
[--savelogin={false|true}]
[--checkports={true|false}]
[--nopassword={false|true}]
domain-name
```

## Description

The `create-domain` subcommand creates a Eclipse GlassFish domain. A domain in Eclipse GlassFish is an administrative namespace that complies with the Java Platform, Enterprise Edition (Jakarta EE) standard. Every domain has a configuration, which is stored in a set of files. Any number of domains, each of which has a distinct administrative identity, can be created in a given installation of Eclipse GlassFish. A domain can exist independently of other domains.

Any user who has access to the `asadmin` utility on a given system can create a domain and store its configuration in a folder of the user's choosing. By default, the domain configuration is created in the default directory for domains. You can override this location to store the configuration elsewhere.

If domain customizers are found in JAR files in the `as-install/modules` directory when the `create-domain` subcommand is run, the customizers are processed. A domain customizer is a class that implements the `DomainInitializer` interface.

The `create-domain` subcommand creates a domain with a single administrative user specified by the `asadmin` utility option `--user`. If the `--user` option is not specified, and the `--nopassword` option is set to true, the default administrative user, `admin`, is used. If the `--nopassword` option is set to false (the default), a username is required. In this case, if you have not specified the user name by using the `--user` option, you are prompted to do so.

You choose an appropriate profile for the domain, depending on the applications that you want to run on your new domain. You can choose the developer, cluster, or enterprise profile for the domain you create.

This subcommand is supported in local mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

### --adminport

The HTTP port or the HTTPS port for administration. This port is the port in the URL that you specify in your web browser to manage the domain, for example, `http://localhost:4949`. The `--adminport` option cannot be used with the `--portbase` option. The default value is 4848.

The `--adminport` option overrides the `domain.adminPort` property of the `--domainproperties` option.

### --instanceport

The domain provides services so that applications can run when deployed. This HTTP port specifies where the web application context roots are available for a web browser to connect to. This port is a positive integer and must be available at the time of domain creation. The `--instanceport` option cannot be used with the `--portbase` option. The default value is 8080.

The `--instanceport` option overrides the `domain.instancePort` property of the `--domainproperties` option.

### --portbase

Determines the number with which port assignments should start. A domain uses a certain number of ports that are statically assigned. The portbase value determines where the assignment should start. The values for the ports are calculated as follows:

- Administration port: portbase + 48
- HTTP listener port: portbase + 80
- HTTPS listener port: portbase + 81
- JMS port: portbase + 76
- IIOP listener port: portbase + 37
- Secure IIOP listener port: portbase + 38
- Secure IIOP with mutual authentication port: portbase + 39
- JMX port: portbase + 86

- JPDA debugger port: portbase + 9
- Felix shell service port for OSGi module management: portbase + 66

When the `--portbase` option is specified, the output of this subcommand includes a complete list of used ports.

The `--portbase` option cannot be used with the `--adminport`, `--instanceport`, or the `--domainproperties` option.

#### **--profile**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

#### **--template**

The file name, including a relative or absolute path, of a domain configuration template to use for creating the domain. If a relative path is specified, the subcommand appends the path to the `as-install/lib/templates` directory to locate the file. If it is an absolute pathname, the subcommand locates the file in the specified path.

This option enables domains of different types to be created and custom domain templates to be defined.

#### **--domaindir**

The directory where the domain is to be created. If specified, the path must be accessible in the filesystem. If not specified, the domain is created in the default domain directory, `as-install/domains`.

#### **--savemasterpassword**

Setting this option to `true` allows the master password to be written to the file system. If this option is `true`, the `--usemasterpassword` option is also true, regardless of the value that is specified on the command line. The default value is `false`.

A master password is really a password for the secure key store. A domain is designed to keep its own certificate (created at the time of domain creation) in a safe place in the configuration location. This certificate is called the domain's SSL server certificate. When the domain is contacted by a web browser over a secure channel (HTTPS), this certificate is presented by the domain. The master password is supposed to protect the store (a file) that contains this certificate. This file is called `keystore.jks` and is created in the configuration directory of the domain created. If however, this option is chosen, the master password is saved on the disk in the domain's configuration location. The master password is stored in a file called `master-password`, which is a Java JCEKS type keystore. The reason for using the `--savemasterpassword` option is for unattended system boots. In this case, the master password is not prompted for when the domain starts because the password will be extracted from this file.

It is best to create a master password when creating a domain, because the master password is used by the `start-domain` subcommand. For security purposes, the default setting should be `false`, because saving the master password on the disk is an insecure practice, unless file system permissions are properly set. If the master password is saved, then `start-domain` does not prompt for it. The master

password gives an extra level of security to the environment.

#### --usemasterpassword

Specifies whether the key store is encrypted with a master password that is built into the system or a user-defined master password.

If `false` (default), the keystore is encrypted with a well-known password that is built into the system. Encrypting the keystore with a password that is built into the system provides no additional security.

If `true`, the subcommand obtains the master password from the `AS_ADMIN_MASTERPASSWORD` entry in the password file or prompts for the master password. The password file is specified in the `--passwordfile` option of the `asadmin(1M)` utility.

If the `--savemasterpassword` option is `true`, this option is also true, regardless of the value that is specified on the command line.

#### --domainproperties

Setting the optional name/value pairs overrides the default values for the properties of the domain to be created. The list must be separated by the colon (:) character. The `--portbase` options cannot be used with the `--domainproperties` option. The following properties are available:

##### `domain.adminPort`

This property specifies the port number of the HTTP port or the HTTPS port for administration. This port is the port in the URL that you specify in your web browser to manage the instance, for example, `http://localhost:4949`. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

The `domain.adminPort` property is overridden by the `--adminport` option.

##### `domain.instancePort`

This property specifies the port number of the port that is used to listen for HTTP requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

The `domain.instancePort` property is overridden by `--instanceport` option.

##### `domain.jmxPort`

This property specifies the port number on which the JMX connector listens. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### `http.ssl.port`

This property specifies the port number of the port that is used to listen for HTTPS requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### `java.debugger.port`

This property specifies the port number of the port that is used for connections to the [Java Platform Debugger Architecture \(JPDA\)](#) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugger. Valid values are 1-65535. On UNIX, creating sockets that listen on

---

ports 1-1024 requires superuser privileges.

#### jms.port

This property specifies the port number for the Java Message Service provider. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

#### orb.listener.port

This property specifies the port number of the port that is used for IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

#### orb.mutualauth.port

This property specifies the port number of the port that is used for secure IIOP connections with client authentication. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

#### orb.ssl.port

This property specifies the port number of the port that is used for secure IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

#### osgi.shell.telnet.port

This property specifies the port number of the port that is used for connections to the [Apache Felix Remote Shell](http://felix.apache.org/site/apache-felix-remote-shell.html) (<http://felix.apache.org/site/apache-felix-remote-shell.html>). This shell uses the Felix shell service to interact with the OSGi module management subsystem. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

#### --keytooloptions

Specifies an optional list of name-value pairs of keytool options for a self-signed server certificate. The certificate is generated during the creation of the domain. Each pair in the list must be separated by the colon (:) character.

Allowed options are as follows:

##### CN

Specifies the common name of the host that is to be used for the self-signed certificate. This option name is case insensitive.

By default, the name is the fully-qualified name of the host where the `create-domain` subcommand is run.

#### --savelogin

If set to true, this option saves the administration user name and password. Default value is false. The username and password are stored in the `.asadminpass` file in user's home directory. A domain can only be created locally. Therefore, when using the `--savelogin` option, the host name saved in `.asadminpass` is always `localhost`. If the user has specified default administration port while creating the domain, there is no need to specify `--user`, `--passwordfile`, `--host`, or `--port` on any of the subsequent `asadmin` remote commands. These values will be obtained automatically.



When the same user creates multiple domains that have the same administration port number on the same or different host (where the home directory is NFS mounted), the subcommand does not ask if the password should be overwritten. The password will always be overwritten.

#### --checkports

Specifies whether to check for the availability of the administration, HTTP, JMS, JMX, and IIOP ports. The default value is true.

#### --nopassword

Specifies whether the administrative user will have a password. If false (the default), the password is specified by the `AS_ADMIN_PASSWORD` entry in the `asadmin` password file (set by using the `--passwordfile` option). If false and the `AS_ADMIN_PASSWORD` is not set, you are prompted for the password.

If true, the administrative user is created without a password. If a user name for the domain is not specified by using the `--user` option, and the `--nopassword` option is set to true, the default user name, `admin`, is used.

## Operands

### domain-name

The name of the domain to be created. The name may contain only ASCII characters and must be a valid directory name for the operating system on the host where the domain is created.

## Examples

### Example 1 Creating a Domain

This example creates a domain named `domain4`.

```

asadmin>create-domain --adminport 4848 domain4
Enter admin user name [Enter to accept default "admin" / no password]>
Using port 4848 for Admin.
Using default port 8080 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Using default port 6666 for OSGI_SHELL.
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=sr1-usca-22,OU=GlassFish,O=Oracle Corp.,L=Redwood Shores,ST=California,C=US]
No domain initializers found, bypassing customization step
Domain domain4 created.
Domain domain4 admin port is 4848.
Domain domain4 allows admin login as user "admin" with no password.
Command create-domain executed successfully.

```

## Example 2 Creating a Domain in an Alternate Directory

This example creates a domain named `sampleDomain` in the `/home/someuser/domains` directory.

```

asadmin> create-domain --domaindir /home/someuser/domains --adminport 7070
--instanceport 7071 sampleDomain
Enter admin user name [Enter to accept default "admin" / no password]>
Using port 7070 for Admin.
Using port 7071 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Using default port 6666 for OSGI_SHELL.
Enterprise Service Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=sr1-usca-22,OU=GlassFish,O=Oracle Corp.,L=Redwood Shores,ST=California,C=US]
No domain initializers found, bypassing customization step
Domain sampleDomain created.
Domain sampleDomain admin port is 7070.
Domain sampleDomain allows admin login as user "admin" with no password.
Command create-domain executed successfully.

```

## Example 3 Creating a Domain and Saving the Administration User Name and Password

This example creates a domain named `myDomain` and saves the administration username and password.

```
asadmin> create-domain --adminport 8282 --savelogin=true myDomain
Enter the admin password [Enter to accept default of no password]>
Enter the master password [Enter to accept default password "changeit"]>
Using port 8282 for Admin.
Using default port 8080 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Using default port 6666 for OSGI_SHELL.
Enterprise ServiceDistinguished Name of the self-signed X.509 Server Certificate is:
[CN=sr1-usca-22,OU=GlassFish,O=Oracle Corp.,L=Redwood Shores,ST=California,C=US]
No domain initializers found, bypassing customization step
Domain myDomain created.
Domain myDomain admin port is 8282.
Domain myDomain allows admin login as user "admin" with no password.
Login information relevant to admin user name [admin]
for this domain [myDomain] stored at
[/home/someuser/.asadminpass] successfully.
Make sure that this file remains protected.
Information stored in this file will be used by
asadmin commands to manage this domain.
Command create-domain executed successfully.
```

## Example 4 Creating a Domain and Designating the Certificate Host

This example creates a domain named `domain5`. The common name of the host that is to be used for the self-signed certificate is `trio`.

```
asadmin> create-domain --adminport 9898 --keytooloptions CN=trio domain5
Enter the admin password [Enter to accept default of no password]>
Enter the master password [Enter to accept default password "changeit"]>
Using port 9898 for Admin.
Using default port 8080 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Using default port 6666 for OSGI_SHELL.
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=trio,OU=GlassFish,O=Oracle Corp.,L=Redwood Shores,ST=California,C=US]
No domain initializers found, bypassing customization step
Domain domain5 created.
Domain domain5 admin port is 9898.
Domain domain5 allows admin login as user "admin" with no password.
Command create-domain executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-domain\(1\)](#), [list-domains\(1\)](#), [login\(1\)](#), [start-domain\(1\)](#), [stop-domain\(1\)](#)

Apache Felix Remote Shell (<http://felix.apache.org/site/apache-felix-remote-shell.html>), Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# create-file-user

Creates a new file user

## Synopsis

```
asadmin [asadmin-options] create-file-user [--help]
[--authrealmnameauth_realm_name]
[--target target]
[--groups user_groups[:user_groups]*] user_name
```

## Description

The `create-file-user` subcommand creates an entry in the keyfile with the specified username, password, and groups. Multiple groups can be created by separating them with a colon (:). If `auth_realm_name` is not specified, an entry is created in the keyfile for the default realm. If `auth_realm_name` is specified, an entry is created in the keyfile using the `auth_realm_name`.

You can use the `--passwordfile` option of the [asadmin\(1M\)](#) command to specify the password for the user. The password file entry must be of the form `AS\_ADMIN\_USERPASSWORD= `user-password.

If a password is not provided, this subcommand fails if secure administration is enabled and the user being created is an administrative user.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

This is the name of the target on which the command operates. The valid targets are config, instance, cluster, or server. By default, the target is the server.

#### --groups

This is the group associated with this file user.

**--authrealmname**

The name of the realm in which the new user is created. If you do not specify this option, the user is created in the "file" realm.

## Operands

**user\_name**

This is the name of file user to be created.

## Examples

### Example 1 Creating a User in the File Realm

This example creates a file realm user named `sample_user`. It is assumed that an authentication realm has already been created using the `create-auth-realm` subcommand.

```
asadmin> create-file-user
--groups staff:manager
--authrealmname auth-realm1 sample_user
Command create-file-user executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-auth-realm\(1\)](#), [delete-file-user\(1\)](#), [list-file-groups\(1\)](#), [list-file-users\(1\)](#), [update-file-user\(1\)](#)

# create-http

Sets HTTP parameters for a protocol

## Synopsis

```
asadmin [asadmin-options] create-http [--help]
--default-virtual-server virtual-server
[--request-timeout-seconds timeout]
[--timeout-seconds timeout]
[--max-connection max-keepalive]
[--dns-lookup-enabled={false|true}]
[--servername server-name]
[--target target]
protocol-name
```

## Description

The `create-http` subcommand creates a set of HTTP parameters for a protocol, which in turn configures one or more network listeners. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --default-virtual-server

The ID attribute of the default virtual server for the associated network listeners.

#### --request-timeout-seconds

The time in seconds at which the request times out. If you do not set this option, the request times out in 30 seconds.

#### --timeout-seconds

The maximum time in seconds for which a keep alive connection is kept open. A value of `0` or less means keep alive connections are kept open indefinitely. The default is `30`.

**--max-connection**

The maximum number of HTTP requests that can be pipelined until the connection is closed by the server. Set this property to `1` to disable HTTP/1.0 keep-alive, as well as HTTP/1.1 keep-alive and pipelining. The default is `256`.

**--dns-lookup-enabled**

If set to `true`, looks up the DNS entry for the client. The default is `false`.

**--servername**

Tells the server what to put in the host name section of any URLs it sends to the client. This affects URLs the server automatically generates; it doesn't affect the URLs for directories and files stored in the server. This name should be the alias name if your server uses an alias. If a colon and port number are appended, that port will be used in URLs that the server sends to the client.

**--target**

Creates the set of HTTP parameters only on the specified target. Valid values are as follows:

**server**

Creates the set of HTTP parameters on the default server instance. This is the default value.

**configuration-name**

Creates the set of HTTP parameters in the specified configuration.

**cluster-name**

Creates the set of HTTP parameters on all server instances in the specified cluster.

**standalone-instance-name**

Creates the set of HTTP parameters on the specified standalone server instance.

# Operands

**protocol-name**

The name of the protocol to which this HTTP parameter set applies.

# Examples

## Example 1 Using the `create-http` Subcommand

The following command creates an HTTP parameter set for the protocol named `http-1`:

```
asadmin> create-http --timeout-seconds 60 --default-virtual-server server http-1
Command create-http executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-network-listener\(1\)](#), [create-protocol\(1\)](#), [create-virtual-server\(1\)](#), [delete-http\(1\)](#)

# create-http-health-checker

Creates a health-checker for a specified load balancer configuration

## Synopsis

```
asadmin [asadmin-options] create-http-health-checker [--help]
[--url "/"]
[--interval 30] [--timeout 10]
[--config config_name] target
```

## Description

The `create-http-health-checker` subcommand creates a health checker for a specified load balancer configuration. A health checker is unique for the combination of target and load balancer configuration.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--url**

The URL to ping to determine whether the instance is healthy.

**--interval**

The interval in seconds the health checker waits between checks of an unhealthy instance to see whether it has become healthy. The default value is 30 seconds. A value of 0 disables the health checker.

**--timeout**

The interval in seconds the health checker waits to receive a response from an instance. If the health checker has not received a response in this interval, the instance is considered unhealthy.

**--config**

The load balancer configuration for which you create the health-checker. If you do not specify a configuration, the subcommand creates a health checker for every load balancer configuration associated with the target. If no configuration references the target, the subcommand fails.

## Operands

**target**

Specifies the target to which the health checker applies.

Valid values are:

- cluster\_name- The name of a target cluster.
- instance\_name- The name of a target server instance.

## Examples

### Example 1 Creating a Health Checker for a Load Balancer Configuration

This example creates a health checker for a load balancer configuration named `mycluster-http-lb-config` on a cluster named `mycluster`.

```
asadmin> create-http-health-checker --config mycluster-http-lb-config mycluster
Command create-http-health-checker executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-http-health-checker\(1\)](#)

# create-http-lb

Creates a load balancer

## Synopsis

```
asadmin [asadmin-options] create-http-lb [--help]
--devicehost device_host_or_IP_address --deviceport device_port
[--sslproxyhost proxy_host]
[--sslproxyport proxy_port] [--target target] [--lbpolicy lbpolicy] [--lbpolicymodule
lb_policy_module] [--healthcheckerurl url]
[--healthcheckerinterval 10] [--healthcheckertimeout 10]
[--lbenableallinstances=true] [--lbenableallapplications=true] [--lbweight
instance=weight[:instance=weight]*] [--responsetimeout 60] [--httpsrouting=false] [--
reloadinterval60][--monitor=false][--routecookie=true]
[--property (name=value)[:name=value]*]
] load_balancer_name
```

## Description

Use the `create-http-lb` subcommand to create a load balancer, including the load balancer configuration, target reference, and health checker. A load balancer is a representation of the actual load balancer device, defined by its device host and port information. Once you've created the load balancer, you can automatically apply changes made to the load balancer configuration without running `export-http-lb-config` and manually copying the generated load balancer configuration file to the web server instance.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

### --devicehost

The device host or the IP address of the load balancing device. This host or IP is where the physical load balancer will reside.

**--deviceport**

The port used to communicate with the load balancing device. It must be SSL enabled.

**--sslproxyhost**

The proxy host used for outbound HTTP.

**--sslproxyport**

The proxy port used for outbound HTTP.

**--target**

Specifies the target to which the load balancer applies.

Valid values are:

- cluster\_name - Specifies that requests for this cluster will be handled by the load balancer.
- stand-alone\_instance\_name - Specifies that requests for this stand-alone instance will be handled by the load balancer.

**--lbpolicy**

The policy the load balancer follows to distribute load to the server instances in a cluster. Valid values are `round-robin`, `weighted-round-robin`, and `user-defined`. If you choose `user-defined`, specify a load balancer policy module with the `lbpolicymodule` option. If you choose `weighted-round-robin`, assign weights to the server instances using the `configure-lb-weight` subcommand. The default is `round-robin`.

**--lbpolicymodule**

If your target is a cluster and the load balancer policy is `user-defined`, use this option to specify the full path and name of the shared library of your load balancing policy module. The shared library needs to be in a location accessible by the web server.

**--healthcheckerurl**

The URL to ping to determine whether the instance is healthy.

**--healthcheckerinterval**

The interval in seconds the health checker waits between checks of an unhealthy instance to see whether it has become healthy. The default value is 10 seconds. A value of 0 disables the health checker.

**--healthcheckertimeout**

The interval in seconds the health checker waits to receive a response from an instance. If the health checker has not received a response in this interval, the instance is considered unhealthy. The default value is 10 seconds.

**--lbenableallinstances**

Enables all instances in the target cluster for load balancing. If the target is a server instance, enables that instance for load balancing.

**--lbenableallapplications**

Enables all applications deployed to the target cluster or instance for load balancing.

**--lbweight**

The name of the instance and the weight you are assigning it. The weight must be an integer. The pairs of instances and weights are separated by colons. For example `instance1=1:instance2=4` means that for every five requests, one goes to instance1 and four go to instance2. A weight of 1 is the default.

**--responsetimeout**

The time in seconds within which a server instance must return a response. If no response is received within the time period, the server is considered unhealthy. If set to a positive number, and the request is idempotent, the request is retried. If the request is not idempotent, an error page is returned. If set to 0 no timeout is used. The default is 60.

**--httpsrouting**

If set to `true`, HTTPS requests to the load balancer result in HTTPS requests to the server instance. If set to `false`, HTTPS requests to the load balancer result in HTTP requests to the server instance. The default is `false`.

**--reloadinterval**

The time, in seconds, that the load balancer takes to check for an updated configuration. When detected, the configuration file is reloaded. The default value is 60 seconds. A value of 0 disables reloading.

**--monitor**

If set to `true`, monitoring of the load balancer is switched on. The default value is `false`.

**--routecookie**

This option is deprecated. The value is always true.

**--property**

Optional attribute name/value pairs for configuring the load balancer.

# Operands

**lb\_name**

The name of the new load balancer. This name must not conflict with any other load balancers in the domain.

# Examples

## Example 1 Creating a Load Balancer

This example creates a load balancer named `mylb`.

```
asadmin> create-http-lb  
--devicehost host1 --deviceport 5555 mylb
```

```
Command create-http-lb executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-http-lb\(1\)](#), [list-http-lbs\(1\)](#), [create-http-lb-config\(1\)](#)

# create-http-lb-config

Creates a configuration for the load balancer

## Synopsis

```
asadmin [asadmin-options] create-http-lb-config [--help]
[--responsetimeout 60]
[httpsrouting=false] [--reloadinterval 60]
[--monitor=false] [--property (name=value)[:name=value]*]
--target target | config_name
```

## Description

Use the [create-http-lb-config](#) subcommand to create a load balancer configuration. This configuration applies to load balancing in the HTTP path. After using this subcommand to create the load balancer configuration file, create the load balancer by running [create-http-lb](#).

You must specify either a target or a configuration name, or both. If you do not specify a target, the configuration is created without a target and you add one later using [create-http-lb-ref](#). If you don't specify a configuration name, a name is created based on the target name. If you specify both, the configuration is created with the specified name, referencing the specified target.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--responsetimeout**

The time in seconds within which a server instance must return a response. If no response is received within the time period, the server is considered unhealthy. If set to a positive number, and the request is idempotent, the request is retried. If the request is not idempotent, an error page is returned. If set to 0 no timeout is used. The default is 60.

**--httpsrouting**

If set to `true`, HTTPS requests to the load balancer result in HTTPS requests to the server instance. If set to `false`, HTTPS requests to the load balancer result in HTTP requests to the server instance. The default is `false`.

**--reloadinterval**

The interval between checks for changes to the load balancer configuration file `loadbalancer.xml`. When the check detects changes, the configuration file is reloaded. A value of `0` disables reloading.

**--monitor**

Specifies whether monitoring is enabled. The default is `false`.

**--routecookie**

This option is deprecated. The value is always `true`.

**--property**

Optional attribute name/value pairs for configuring the load balancer.

**--target**

Specifies the target to which the load balancer configuration applies. If you don't specify a target, the load balancer configuration is created without a target. You can specify targets later using the subcommand `create-http-lb-ref`.

Valid values are:

- `cluster_name`- Specifies that requests for this cluster will be handled by the load balancer.
- `stand-alone_instance_name`- Specifies that requests for this standalone instance will be handled by the load balancer.

## Operands

**config\_name**

The name of the new load balancer configuration. This name must not conflict with any other load balancer groups, agents, configurations, clusters, or sever instances in the domain. If you don't specify a name, the load balancer configuration name is based on the target name, `target_name`-http-lb-config``.

## Examples

### Example 1 Creating a Load Balancer Configuration

This example creates a load balancer configuration on a target named `mycluster` and load balancer configuration named `mylbconfigname`.

```
asadmin> create-http-lb-config --target mycluster mylbconfigname
```

```
Command create-http-lb-config executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-http-lb-config\(1\)](#), [list-http-lb-configs\(1\)](#), [create-http-lb\(1\)](#)

# create-http-lb-ref

Adds an existing cluster or server instance to an existing load balancer configuration or load balancer

## Synopsis

```
asadmin [asadmin-options] create-http-lb-ref [--help]
--config config_name | --lbname load_balancer_name
[--lbpolicy round-robin] [--lbpolicymodule lb_policy_module]
[--healthcheckerurl url] [--healthcheckerinterval 10]
[--healthcheckertimeout 10] [--lbenableallinstances=true]
[--lbenableallapplications=true] [--lbweight instance=weight[:instance=weight]*]
target
```

## Description

Use the `create-http-lb-ref` subcommand to:

- Add an existing cluster or server instance to an existing load balancer configuration or load balancer. The load balancer forwards the requests to the clustered and standalone instances it references.
- Set the load balancing policy to round-robin, weighted round-robin, or to a user-defined policy.
- Configure a health checker for the load balancer. Any health checker settings defined here apply only to the target. If you do not create a health checker with this subcommand, use `create-http-health-checker`.
- Enable all instances in the target cluster for load balancing, or use `enable-http-lb-server` to enable them individually.
- Enable all applications deployed to the target for load balancing, or use `enable-http-lb-application` to enable them individually.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--config**

Specifies which load balancer configuration to which to add clusters and server instances. Specify either a load balancer configuration or a load balancer. Specifying both results in an error.

**--lbname**

Specifies the load balancer to which to add clusters and server instances. Specify either a load balancer configuration or a load balancer. Specifying both results in an error.

**--lbpolicy**

The policy the load balancer follows. Valid values are `round-robin`, `weighted-round-robin`, and `user-defined`. If you choose user-defined, specify a load balancer policy module with the `lbpolymodule` option. If you choose `weighted-round-robin` assign weights to the server instances using the `configure-lb-weight` subcommand. The default is `round-robin`.

**--lbpolymodule**

If your load balancer policy is `user-defined`, use this option to specify the full path and name of the shared library of your load balancing policy module. The shared library needs to be in a location accessible by the web server.

**--healthcheckerurl**

The URL to ping to determine whether the instance is healthy.

**--healthcheckerinterval**

The interval in seconds the health checker waits between checks of an unhealthy instance to see whether it has become healthy. The default value is 30 seconds. A value of 0 disables the health checker.

**--healthcheckertimeout**

The interval in seconds the health checker waits to receive a response from an instance. If the health checker has not received a response in this interval, the instance is considered unhealthy. The default is 10.

**--lbenableallinstances**

Enables all instances in the target cluster for load balancing. If the target is a server instance, enables that instance for load balancing. The default value is true.

**--lbenableallapplications**

Enables all applications deployed to the target cluster or instance for load balancing. The default value is true.

**--lbweight**

The name of the instance and the weight you are assigning it. The weight must be an integer. The pairs of instances and weights are separated by colons. For example `instance1=1:instance2=4` means that for every five requests, one goes to instance1 and four go to instance2. A weight of 1 is the default.

## Operands

**target**

Specifies which cluster or instance to add to the load balancer. Valid values are:

- `cluster_name`- Specifies that requests for this cluster will be handled by the load balancer.
- `stand-alone_instance_name`- Specifies that requests for this standalone instance will be handled by the load balancer.

## Examples

### Example 1 Adding a Cluster Reference to a Load Balancer Configuration

This example adds a reference to a cluster named `cluster2` to a load balancer configuration named `mylbconfig`.

```
asadmin> create-http-lb-ref --config mylbconfig cluster2
```

```
Command create-http-lb-ref executed successfully.
```

### Example 2 Adding a Cluster Reference to a Load Balancer

This example adds a reference to a cluster named `cluster2` to a load balancer named `mylb`.

```
asadmin> create-http-lb-ref --lbname mylb cluster2
```

```
Command create-http-lb-ref executed successfully.
```

## Example 3 Configuring a Health Checker and Load Balancer Policy

This example configures a health checker and load balancing policy, and enables the load balancer for instances and applications.

```
asadmin> create-http-lb-ref --config mylbconfig --lbpolicy weighted-round-robin  
--healthcheckerinterval 40 --healthcheckertimeout 20  
--lbenableallinstances=true --lbenableallapplications=true cluster2
```

Command create-http-lb-ref executed successfully.

## Example 4 Setting a User-Defined Load Balancing Policy

This example sets a user-defined load balancing policy.

```
asadmin> create-http-lb-ref --lbpolicy user-defined --lbpolymodule  
/user/modules/module.so  
--config mylbconfig cluster2
```

Command create-http-lb-ref executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[configure-lb-weight\(1\)](#), [create-http-health-checker\(1\)](#), [delete-http-lb-ref\(1\)](#), [enable-http-lb-application\(1\)](#), [enable-http-lb-server\(1\)](#), [list-http-lb-configs\(1\)](#), [list-http-lbs\(1\)](#)

# create-http-listener

Adds a new HTTP network listener socket

## Synopsis

```
asadmin [asadmin-options] create-http-listener [--help]
--listeneraddress address
--listenerport listener-port
[--default-virtual-server | --defaultvs} virtual-server
[--servername server-name]
[--acceptorthreads acceptor-threads]
[--xpowered={true|false}]
[--redirectport redirect-port]
[--securityenabled={false|true}]
[--enabled={true|false}]
[--target target]
listener-id
```

## Description

The `create-http-listener` subcommand creates an HTTP network listener. This subcommand is supported in remote mode only.



If you edit the special HTTP network listener named `admin-listener`, you must restart the server for the changes to take effect. The Administration Console does not tell you that a restart is required in this case.



This subcommand is provided for backward compatibility and as a shortcut for creating network listeners that use the HTTP protocol. Behind the scenes, this subcommand creates a network listener and its associated protocol, transport, and HTTP configuration.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--listeneraddress**

The IP address or the hostname (resolvable by DNS).

**--listenerport**

The port number to create the listen socket on. Legal values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges. Configuring an SSL listen socket to listen on port 443 is recommended.

**--default-virtual-server****--defaultvts**

The ID attribute of the default virtual server for this listener. The **--defaultvts** option is deprecated.

**--servername**

Tells the server what to put in the host name section of any URLs it sends to the client. This affects URLs the server automatically generates; it doesn't affect the URLs for directories and files stored in the server. This name should be the alias name if your server uses an alias. If a colon and port number are appended, that port will be used in URLs that the server sends to the client.

**--acceptorthreads**

The number of acceptor threads for the listener socket. The recommended value is the number of processors in the machine. The default value is 1.

**--xpowered**

If set to `true`, adds the `X-Powered-By: Servlet/3.0` and `X-Powered-By: JSP/2.0` headers to the appropriate responses. The Servlet 3.0 specification defines the `X-Powered-By: Servlet/3.0` header, which containers may add to servlet-generated responses. Similarly, the JSP 2.0 specification defines the `X-Powered-By: JSP/2.0` header, which containers may add to responses that use JSP technology. The goal of these headers is to aid in gathering statistical data about the use of Servlet and JSP technology. The default value is `true`.

**--redirectport**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--securityenabled**

If set to `true`, the HTTP listener runs SSL. You can turn SSL2 or SSL3 ON or OFF and set ciphers using an `SSL` element. The security setting globally enables or disables SSL by making certificates available to the server instance. The default value is `false`.

**--enabled**

If set to `true`, the listener is enabled at runtime. The default value is `true`.

**--target**

Creates the HTTP listener only on the specified target. Valid values are as follows:

**server**

Creates the HTTP listener on the default server instance. This is the default value.

**configuration-name**

Creates the HTTP listener in the specified configuration.

**cluster-name**

Creates the HTTP listener on all server instances in the specified cluster.

**standalone-instance-name**

Creates the HTTP listener on the specified standalone server instance.

## Operands

**listener-id**

The listener ID of the HTTP network listener.

## Examples

### Example 1 Creating an HTTP Network Listener

The following command creates an HTTP network listener named `sampleListener` that uses a nondefault number of acceptor threads and is not enabled at runtime:

```
asadmin> create-http-listener --listeneraddress 0.0.0.0 --listenerport 7272  
--defaultvs server --servername host1.sun.com --acceptorthreads 100  
--securityenabled=false --enabled=false sampleListener  
Command create-http-listener executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[create-ssl\(1\)](#), [create-network-listener\(1\)](#), [create-virtual-server\(1\)](#), [delete-http-listener\(1\)](#), [list-http-listeners\(1\)](#)

# create-http-redirect

Adds a new HTTP redirect

## Synopsis

```
asadmin [asadmin-options] create-http-redirect [--help]
[--redirect-port redirect-port]
[--secure-redirect={false|true}]
[--target target]
protocol-name
```

## Description

The `create-http-redirect` subcommand creates an HTTP redirect. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --redirect-port

Port number for redirects. If the HTTP listener is supporting non-SSL requests, and a request is received for which a matching security-constraint requires SSL transport, Eclipse GlassFish automatically redirects the request to this port number.

#### --secure-redirect

If set to true, the HTTP redirect runs SSL. The default value is `false`.

#### --target

Creates the HTTP redirect only on the specified target. Valid values are as follows:

##### server

Creates the HTTP redirect on the default server instance. This is the default value.

##### configuration-name

Creates the HTTP redirect in the specified configuration.

**cluster-name**

Creates the HTTP redirect on all server instances in the specified cluster.

**standalone-instance-name**

Creates the HTTP redirect on the specified standalone server instance.

# Operands

**protocol-name**

The name of the protocol to which to apply the redirect.

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[delete-http-redirect\(1\)](#)

# create-iiop-listener

Adds an IIOP listener

## Synopsis

```
asadmin [asadmin-options] create-iiop-listener [--help]
--listeneraddress address
[--iiopport iiop-port-number] [--securityenabled={false|true}] [--enabled={true|false}]
[--property (name=value)[:name=value]*]
[--target target] listener_id
```

## Description

The `create-iiop-listener` subcommand creates an IIOP listener. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --listeneraddress

Either the IP address or the hostname (resolvable by DNS).

#### --iiopport

The IIOP port number. The default value is 1072.

#### --securityenabled

If set to true, the IIOP listener runs SSL. You can turn SSL2 or SSL3 ON or OFF and set ciphers using an SSL element. The security setting globally enables or disables SSL by making certificates available to the server instance. The default value is `false`.

#### --enabled

If set to true, the IIOP listener is enabled at runtime. The default value is `true`.

#### --property

Optional attribute name/value pairs for configuring the IIOP listener.

**--target**

Specifies the target for which you are creating the IIOP listener. Valid values are

**server**

Creates the listener for the default server instance **server** and is the default value.

**configuration\_name**

Creates the listener for the named configuration.

**cluster\_name**

Creates the listener for every server instance in the cluster.

**stand-alone\_instance\_name**

Creates the listener for a particular standalone server instance.

## Operands

**listener\_id**

A unique identifier for the IIOP listener to be created.

## Examples

### Example 1 Creating an IIOP Listener

The following command creates an IIOP listener named **sample\_iop\_listener**:

```
asadmin> create-iiop-listener --listeneraddress 192.168.1.100
--iiopport 1400 sample_iop_listener
Command create-iiop-listener executed successfully.
```

### Example 2 Creating an IIOP Listener with a Target Cluster

The following command creates an IIOP listener named **iop\_listener\_2** for the cluster **mycluster**. It uses the target option.

```
asadmin> create-iiop-listener --listeneraddress 0.0.0.0 --iiopport 1401
--target mycluster iop_listener_2
Command create-iiop-listener executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-ssl\(1\)](#), [delete-iiop-listener\(1\)](#), [list-iiop-listeners\(1\)](#)

# create-instance

Creates a Eclipse GlassFish instance

## Synopsis

```
asadmin [asadmin-options] create-instance [--help]
--node node-name
[--config config-name | --cluster cluster-name]
[--lbenabled={true|false}]
[--portbase=port-number] [--checkports={true|false}]
[--systemproperties (name=value)[:name=value]* ]
instance-name
```

## Description

The `create-instance` subcommand creates a Eclipse GlassFish instance. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured on the host where the domain administration server (DAS) is running and on the host that is represented by the node where the instance is to reside.



DCOM or SSH is not required if the instance is to reside on a node of type `CONFIG` that represents the local host. A node of type `CONFIG` is not enabled for remote communication over DCOM or SSH.

You may run this command from any host that can contact the DAS.

A Eclipse GlassFish instance is a single Virtual Machine for the Java platform (Java Virtual Machine or JVM machine) on a single node in which Eclipse GlassFish is running. A node defines the host where the Eclipse GlassFish instance resides. The JVM machine must be compatible with the Java Platform, Enterprise Edition (Jakarta EE).

A Eclipse GlassFish instance requires a reference to the following items:

- The node that defines the host where the instance resides. The node must be specified in the command to create the instance.
- The named configuration that defines the configuration of the instance. The configuration can be specified in the command to create the instance, but is not required. If no configuration is specified for an instance that is not joining a cluster, the subcommand creates a configuration for the instance. An instance that is joining a cluster receives its configuration from its parent cluster.

Each Eclipse GlassFish instance is one of the following types of instance:

## Standalone instance

A standalone instance does not share its configuration with any other instances or clusters. A standalone instance is created if either of the following conditions is met:

- No configuration or cluster is specified in the command to create the instance.
- A configuration that is not referenced by any other instances or clusters is specified in the command to create the instance.

When no configuration or cluster is specified, a copy of the `default-config` configuration is created for the instance. The name of this configuration is `instance-name-config`, where `instance-name` represents the name of an unclustered server instance.

## Shared instance

A shared instance shares its configuration with other instances or clusters. A shared instance is created if a configuration that is referenced by other instances or clusters is specified in the command to create the instance.

## Clustered instance

A clustered instance inherits its configuration from the cluster to which the instance belongs and shares its configuration with other instances in the cluster. A clustered instance is created if a cluster is specified in the command to create the instance.

Any instance that is not part of a cluster is considered an unclustered server instance. Therefore, standalone instances and shared instances are unclustered server instances.

By default, this subcommand attempts to resolve possible port conflicts for the instance that is being created. The subcommand also assigns ports that are currently not in use and not already assigned to other instances on the same node. The subcommand assigns these ports on the basis of an algorithm that is internal to the subcommand. Use the `--systemproperties` option to resolve port conflicts for additional instances on the same node. System properties of an instance can be manipulated by using the `create-system-properties(1)` subcommand and the `delete-system-property(1)` subcommand.

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--node`

The name of the node that defines the host where the instance is to be created. The node must

already exist. If the instance is to be created on the host where the domain administration server (DAS) is running, use the predefined node `localhost`-domain.

#### --config

Specifies the named configuration that the instance references. The configuration must exist and must not be named `default-config` or `server-config`. Specifying the `--config` option creates a shared instance.

The `--config` option and the `--cluster` option are mutually exclusive. If both options are omitted, a standalone instance is created.

#### --cluster

Specifies the cluster from which the instance inherits its configuration. Specifying the `--cluster` option creates a clustered instance.

The `--config` option and the `--cluster` option are mutually exclusive. If both options are omitted, a standalone instance is created.

#### --lbenabled

Specifies whether the instance is enabled for load balancing. Possible values are as follows:

##### true

The instance is enabled for load balancing (default).

When an instance is enabled for load balancing, a load balancer sends requests to the instance.

##### false

The instance is disabled for load balancing.

When an instance is disabled for load balancing, a load balancer does not send requests to the instance.

#### --portbase

Determines the number with which the port assignment should start. An instance uses a certain number of ports that are statically assigned. The portbase value determines where the assignment should start. The values for the ports are calculated as follows:

- Administration port: portbase + 48
- HTTP listener port: portbase + 80
- HTTPS listener port: portbase + 81
- JMS port: portbase + 76
- IIOP listener port: portbase + 37
- Secure IIOP listener port: portbase + 38
- Secure IIOP with mutual authentication port: portbase + 39
- JMX port: portbase + 86
- JPA debugger port: portbase + 9

- Felix shell service port for OSGi module management: portbase + 66

When the `--portbase` option is specified, the output of this subcommand includes a complete list of used ports.

#### --checkports

Specifies whether to check for the availability of the administration, HTTP, JMS, JMX, and IIOP ports. The default value is `true`.

#### --systemproperties

Defines system properties for the instance. These properties override property definitions for port settings in the instance's configuration. Predefined port settings must be overridden if, for example, two clustered instances reside on the same host. In this situation, port settings for one instance must be overridden because both instances share the same configuration.

The following properties are available:

##### **ASADMIN\_LISTENER\_PORT**

This property specifies the port number of the HTTP port or HTTPS port through which the DAS connects to the instance to manage the instance. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### **HTTP\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTP requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### **HTTP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTPS requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### **IIOP\_LISTENER\_PORT**

This property specifies the port number of the port that is used for IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### **IIOP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

##### **IIOP\_SSL\_MUTUALAUTH\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections with client authentication. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## JAVA\_DEBUGGER\_PORT

This property specifies the port number of the port that is used for connections to the Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugger. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## JMS\_PROVIDER\_PORT

This property specifies the port number for the Java Message Service provider. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## JMX\_SYSTEM\_CONNECTOR\_PORT

This property specifies the port number on which the JMX connector listens. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## OSGI\_SHELL\_TELNET\_PORT

This property specifies the port number of the port that is used for connections to the Apache Felix Remote Shell (<http://felix.apache.org/site/apache-felix-remote-shell.html>). This shell uses the Felix shell service to interact with the OSGi module management subsystem. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

# Operands

## instance-name

The name of the instance that is being created.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period
  - Underscore
- The name must be unique in the domain and must not be the name of another Eclipse GlassFish instance, a cluster, a named configuration, or a node.
- The name must not be **domain**, **server**, or any other keyword that is reserved by Eclipse GlassFish.

# Examples

## Example 1 Creating a Standalone Eclipse GlassFish Instance

This example creates the standalone Eclipse GlassFish instance `pmdsainst` in the domain `domain1` on the local host.

```
asadmin> create-instance --node localhost-domain1 pmdsainst
Port Assignments for server instance pmdsainst:
JMX_SYSTEM_CONNECTOR_PORT=28688
JMS_PROVIDER_PORT=27678
ASADMIN_LISTENER_PORT=24850
HTTP_LISTENER_PORT=28082
IIOP_LISTENER_PORT=23702
IIOP_SSL_LISTENER_PORT=23822
HTTP_SSL_LISTENER_PORT=28183
IIOP_SSL_MUTUALAUTH_PORT=23922
```

Command `create-instance` executed successfully.

## Example 2 Creating a Standalone Eclipse GlassFish Instance With Custom Port Assignments

### Port Assignments

This example creates the standalone Eclipse GlassFish instance `pmdcpinst` in the domain `domain1` on the local host. Custom port numbers are assigned to the following ports:

- HTTP listener port
- HTTPS listener port
- IIOP connections port
- Secure IIOP connections port
- Secure IIOP connections port with mutual authentication
- JMX connector port

```
asadmin> create-instance --node localhost-domain1
--systemproperties HTTP_LISTENER_PORT=58294:
HTTP_SSL_LISTENER_PORT=58297:
IIOP_LISTENER_PORT=58300:
IIOP_SSL_LISTENER_PORT=58303:
IIOP_SSL_MUTUALAUTH_PORT=58306:
JMX_SYSTEM_CONNECTOR_PORT=58309 pmdcpinst
Port Assignments for server instance pmdcpinst:
JMS_PROVIDER_PORT=27679
ASADMIN_LISTENER_PORT=24851
```

Command create-instance executed successfully.

### Example 3 Creating a Shared Eclipse GlassFish Instance

This example creates the shared Eclipse GlassFish instance `pmdsharedinst1` in the domain `domain1` on the local host. The shared configuration of this instance is `pmdsharedconfig`.

```
asadmin create-instance --node localhost-domain1 --config pmdsharedconfig
pmdsharedinst1
Port Assignments for server instance pmdsharedinst1:
JMX_SYSTEM_CONNECTOR_PORT=28687
JMS_PROVIDER_PORT=27677
ASADMIN_LISTENER_PORT=24849
HTTP_LISTENER_PORT=28081
IIOP_LISTENER_PORT=23701
IIOP_SSL_LISTENER_PORT=23821
HTTP_SSL_LISTENER_PORT=28182
IIOP_SSL_MUTUALAUTH_PORT=23921
```

Command create-instance executed successfully.

### Example 4 Creating a Clustered Eclipse GlassFish Instance

This example creates the clustered Eclipse GlassFish instance `pmdinst1` in the domain `domain1` on the local host. The instance is a member of the cluster `pmdclust1`.

```
asadmin> create-instance --node localhost-domain1 --cluster pmdclust pmdinst1
Port Assignments for server instance pmdinst1:
JMX_SYSTEM_CONNECTOR_PORT=28686
JMS_PROVIDER_PORT=27676
HTTP_LISTENER_PORT=28080
ASADMIN_LISTENER_PORT=24848
IIOP_SSL_LISTENER_PORT=23820
IIOP_LISTENER_PORT=23700
HTTP_SSL_LISTENER_PORT=28181
IIOP_SSL_MUTUALAUTH_PORT=23920
```

Command create-instance executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-local-instance\(1\)](#), [create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [create-system-properties\(1\)](#), [delete-instance\(1\)](#), [delete-system-property\(1\)](#), [list-instances\(1\)](#), [setup-ssh\(1\)](#), [start-instance\(1\)](#), [stop-instance\(1\)](#)

# create-jacc-provider

Enables administrators to create a JACC provider that can be used by third-party authorization modules for applications running in Eclipse GlassFish

## Synopsis

```
asadmin [asadmin-options] create-jacc-provider [--help]
[--policyproviderclass pol-provider-class]
[--policyconfigfactoryclass pc-factory-class]
[--property name=value)[:name=value]*]
[--target target] jacc-provider-name
```

## Description

The `create-jacc-provider` subcommand creates a JSR-115—compliant Java Authorization Contract for Containers (JACC) provider that can be used for authorization of applications running in Eclipse GlassFish. The JACC provider is created as a `jacc-provider` element within the `security-service` element in the domain's `domain.xml` file.

The default Eclipse GlassFish installation includes two JACC providers, named `default` and `simple`. Any JACC providers created with the `create-jacc-provider` subcommand are in addition to these two default providers. The default Eclipse GlassFish JACC providers implement a simple, file-based authorization engine that complies with the JACC specification. The `create-jacc-provider` subcommand makes it possible to specify additional third-party JACC providers.

You can create any number of JACC providers within the `security-service` element, but the Eclipse GlassFish runtime uses only one of them at any given time. The `jacc-provider` element in the `security-service` element points to the name of the provider that is currently in use by Eclipse GlassFish. If you change this element to point to a different JACC provider, restart Eclipse GlassFish.

This command is supported in remote mode only.

## Options

If an option has a short option name, then the short option precedes the long option name. Short options have one dash whereas long options have two dashes.

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--policyproviderclass**

Specifies the fully qualified class name for the `javax.security.jacc.policy.provider` that implements the `java.security.Policy`.

**--policyconfigfactoryclass**

Specifies the fully qualified class name for the `javax.security.jacc.PolicyConfigurationFactory.provider` that implements the provider-specific `javax.security.jacc.PolicyConfigurationFactory`.

**--property**

Optional attribute name/value pairs for configuring the JACC provider. The following properties are available:

**repository**

The directory containing the JACC policy file. For the `default` Eclipse GlassFish JACC provider, the default directory is `#{com.sun.aas.instanceRoot}/generated/policy`. This property is not defined by default for the `simple` Eclipse GlassFish JACC provider.

**--target**

Specifies the target for which you are creating the JACC provider. The following values are valid:

**server**

Creates the JACC provider on the default server instance. This is the default value.

**configuration\_name**

Creates the JACC provider in the specified configuration.

**cluster\_name**

Creates the JACC provider on all server instances in the specified cluster.

**instance\_name**

Creates the JACC provider on a specified server instance.

# Operands

**jacc-provider-name**

The name of the provider used to reference the `jacc-provider` element in `domain.xml`.

# Examples

## Example 1 Creating a JACC Provider

The following example shows how to create a JACC provider named `testJACC` on the default `server` target.

```
asadmin> create-jacc-provider  
--policyproviderclass org.glassfish.exousia.modules.locked.SimplePolicyProvider  
--policyconfigfactoryclass  
org.glassfish.exousia.modules.locked.SimplePolicyConfigurationFactory  
testJACC
```

Command `create-jacc-provider` executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-jacc-provider\(1\)](#), [list-jacc-providers\(1\)](#)

# create-javamail-resource

Creates a JavaMail session resource

## Synopsis

```
asadmin [asadmin-options] create-javamail-resource [--help]
[--target target] --mailhost hostname
--mailuser username --fromaddress address [--storeprotocol storeprotocol]
[--storeprotocolclass storeprotocolclass] [--transprotocol transprotocol]
[--transprotocolclass transprotocolclass] [--debug={false|true}] [--enabled={true|false}]
[--description resource-description] [--property (name=value)[:name=value]*] jndi-name
```

## Description

The `create-javamail-resource` subcommand creates a JavaMail session resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target for which you are creating the JavaMail session resource. Valid values are:

##### server

Creates the resource for the default server instance. This is the default value.

##### domain

Creates the resource for the domain.

##### cluster\_name

Creates the resource for every server instance in the cluster.

**instance\_name**

Creates the resource for a particular server instance.

**--mailhost**

The DNS name of the default mail server. The connect methods of the Store and Transport objects use this value if a protocol-specific host property is not supplied. The name must be resolvable to an actual host name.

**--mailuser**

The name of the mail account user provided when connecting to a mail server. The connect methods of the Store and Transport objects use this value if a protocol-specific username property is not supplied.

**--fromaddress**

The email address of the default user, in the form `username`@host.`domain`.

**--storeprotocol**

The mail server store protocol. The default is `imap`. Change this value only if you have reconfigured the Eclipse GlassFish's mail provider to use a non-default store protocol.

**--storeprotocolclass**

The mail server store protocol class name. The default is `com.sun.mail.imap.IMAPStore`. Change this value only if you have reconfigured the Eclipse GlassFish's mail provider to use a nondefault store protocol.

**--transprotocol**

The mail server transport protocol. The default is `smtp`. Change this value only if you have reconfigured the Eclipse GlassFish's mail provider to use a nondefault transport protocol.

**--transprotocolclass**

The mail server transport protocol class name. The default is `com.sun.mail.smtp.SMTPTransport`. Change this value only if you have reconfigured the Eclipse GlassFish's mail provider to use a nondefault transport protocol.

**--debug**

If set to true, the server starts up in debug mode for this resource. If the JavaMail log level is set to `FINE` or `FINER`, the debugging output will be generated and will be included in the server log file. The default value is false.

**--enabled**

If set to true, the resource is enabled at runtime. The default value is true.

**--description**

Text providing some details of the JavaMail resource.

**--property**

Optional attribute name/value pairs for configuring the JavaMail resource. The Eclipse GlassFish-specific `mail-` prefix is converted to the standard mail prefix. The JavaMail API documentation lists the properties you might want to set.

## Operands

### jndi-name

The JNDI name of the JavaMail resource to be created. It is a recommended practice to use the naming subcontext prefix `mail/` for JavaMail resources.

## Examples

### Example 1 Creating a JavaMail Resource

This example creates a JavaMail resource named `mail/MyMailSession`. The JNDI name for a JavaMail session resource customarily includes the `mail/` naming subcontext.

```
asadmin> create-javamail-resource --mailhost localhost  
--mailuser sample --fromaddress sample@sun.com mail/MyMailSession  
Command create-javamail-resource executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-javamail-resource\(1\)](#), [list-javamail-resources\(1\)](#)

# create-jdbc-connection-pool

Registers a JDBC connection pool

## Synopsis

```
asadmin [asadmin-options] create-jdbc-connection-pool [--help]
[--datasourceclassname=datasourceclassname]
[--restype=resourcetype]
[--steadypoolsize=poolsiz]
[--maxpoolsize=maxpoolsize]
[--maxwait=maxwaittime]
[--poolresize=poolresizelimit]
[--idletimeout=idletimeout]
[--initsql=initsqlstring]
[--isolationlevel=isolationlevel]
[--isisolationguaranteed={true|false}]
[--isconnectvalidatereq={false|true}]
[--validationmethod=validationmethod]
[--validationtable=validationtable]
[--failconnection={false|true}]
[--allownoncomponentcallers={false|true}]
[--nontransactionalconnections={false|true}]
[--validateatmostonceperiod=validationinterval]
[--leaktimeout=leaktimeout]
[--leakreclaim={false|true}]
[--statementleaktimeout=satementleaktimeout]
[--statmentleakreclaim={false|true}]
[--creationretryattempts=creationretryattempts]
[--creationretryinterval=creationretryinterval]
[--sqltracelisteners=sqltracelisteners[,sqltracelisteners]]
[--statementtimeout=statementtimeout]
[--lazyconnectionenlistment={false|true}]
[--lazyconnectionassociation={false|true}]
[--associatewiththread={false|true}]
[--driverclassname=jdbcdriverclassname]
[--matchconnections={false|true}]
[--maxconnectionusagecount=maxconnectionusagecount]
[--ping={false|true}]
[--pooling={false|true}]
[--statementcachesize=statementcachesize]
[--validationclassname=validationclassname]
[--wrapjdbcobjects={false|true}]
[--description description]
[--property name=value)[:name=value]*]
[--target=target]
connectionpoolid
```

## Description

The `create-jdbc-connection-pool` subcommand registers a new Java Database Connectivity ("JDBC")

---

software connection pool with the specified JDBC connection pool name.

A JDBC connection pool with authentication can be created either by using a **--property** option to specify user, password, or other connection information, or by specifying the connection information in the XML descriptor file.

This subcommand is supported in remote mode only.

## Options

### **asadmin-options**

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### **--help**

**-?**

Displays the help text for the subcommand.

#### **--datasourceclassname**

The name of the vendor-supplied JDBC datasource resource manager. An XA or global transactions capable datasource class will implement the `javax.sql.XADatasource` interface. Non-XA or exclusively local transaction datasources will implement the `javax.sql.Datasource` interface.

#### **--restype**

Required when a datasource class implements two or more interfaces (`javax.sql.DataSource`, `javax.sql.XADataSource`, or `javax.sql.ConnectionPoolDataSource`), or when a driver classname must

#### **be provided.**

- If `--restype = java.sql.Driver`, then the `--driverclassname` option is required.
- If `--restype = javax.sql.DataSource, javax.sql.XADataSource, or javax.sql.ConnectionPoolDataSource`, then the `--datasourceclassname` option is required.
- If `--restype` is not specified, then either the `--driverclassname` or `--datasourceclassname` option must be specified, but not both.

#### **--steadypoolsize**

The minimum and initial number of connections maintained in the pool. The default value is 8.

#### **--maxpoolsize**

The maximum number of connections that can be created. The default value is 32.

#### **--maxwait**

The amount of time, in milliseconds, that a caller will wait before a connection timeout is sent. The default is 60000 (60 seconds). A value of 0 forces the caller to wait indefinitely.

**--poolresize**

Number of connections to be removed when `idle-timeout-in-seconds` timer expires. This is the quantity by which the pool will scale up or scale down the number of connections. Scale up: When the pool has no free connections, pool will scale up by this quantity. Scale down: All the invalid and idle connections are removed, sometimes resulting in removing connections of quantity greater than this value. Connections that have been idle for longer than the timeout are candidates for removal. Steadypoolsize will be ensured. Possible values are from 0 to `MAX_INTEGER`. The default value is 2.

**--idletimeout**

The maximum time, in seconds, that a connection can remain idle in the pool. After this time, the implementation can close this connection. This timeout value must be kept shorter than the database server side timeout value to prevent the accumulation of unusable connections in the application. The default value is 300.

**--initsql**

An SQL string that is executed whenever a connection is created from the pool. If an existing connection is reused, this string is not executed. Connections that have idled for longer than the timeout are candidates for removal. This option has no default value.

**--isolationlevel**

The transaction-isolation-level on the pooled database connections. This option does not have a default value. If not specified, the pool operates with the default isolation level that the JDBC driver provides. You can set a desired isolation level using one of the standard transaction isolation levels: `read-uncommitted`, `read-committed`, `repeatable-read`, `serializable`. Applications that change the isolation level on a pooled connection programmatically risk polluting the pool. This could lead to program errors.

**--isisolationguaranteed**

This is applicable only when a particular isolation level is specified for transaction-isolation-level. The default value is true.

This option assures that every time a connection is obtained from the pool, isolation level is set to the desired value. This could have some performance impact on some JDBC drivers. Administrators can set this to false when the application does not change `--isolationlevel` before returning the connection.

**--isconnectvalidatereq**

If set to true, connections are validated or checked to see if they are usable before giving out to the application. The default value is false.

**--validationmethod**

Type of validation to be performed when `is-connection-validation-required` is true. Valid settings are: `auto-commit`, `meta-data`, `table`, or `custom-validation`. The default value is `table`.

**--validationtable**

The name of the validation table used to perform a query to validate a connection. If **is-connection-validation-required** is set to true and connection-validation-type set to table, this option is mandatory.

**--failconnection**

If set to true, all connections in the pool must be closed when a single validation check fails. The default value is false. One attempt is made to reestablish failed connections.

**--allownoncomponentcallers**

A pool with this property set to true can be used by non-Jakarta EE components, that is, components other than EJBs or Servlets. The returned connection is enlisted automatically with the transaction context obtained from the transaction manager. Connections obtained by non-component callers are not automatically cleaned by the container at the end of a transaction. These connections need to be explicitly closed by the caller.

**--nontransactionalconnections**

A pool with this property set to true returns non-transactional connections. This connection does not get automatically enlisted with the transaction manager.

**--validateatmostonceperiod**

Specifies the time interval in seconds between successive requests to validate a connection at most once. Setting this attribute to an appropriate value minimizes the number of validation requests by a connection. Default value is 0, which means that the attribute is not enabled.

**--leaktimeout**

Specifies the amount of time, in seconds, for which connection leaks in a connection pool are to be traced. When a connection is not returned to the pool by the application within the specified period, it is assumed to be a potential leak, and stack trace of the caller will be logged. This option only detects if there is a connection leak. The connection can be reclaimed only if **connection-leak-reclaim** is set to true.

If connection leak tracing is enabled, you can use the Administration Console to enable monitoring of the JDBC connection pool to get statistics on the number of connection leaks. The default value is 0, which disables connection leak tracing.

**--leakreclaim**

Specifies whether leaked connections are restored to the connection pool after leak connection tracing is complete. Possible values are as follows:

**false**

Leaked connections are not restored to the connection pool (default).

**true**

Leaked connections are restored to the connection pool.

**--statementleaktimeout**

Specifies the amount of time, in seconds, after which any statements that have not been closed by an application are to be detected. Applications can run out of cursors if statement objects are not properly closed. This option only detects if there is a statement leak. The statement can be reclaimed only if `statement-leak-reclaim` is set to true. The leaked statement is closed when it is reclaimed.

The stack trace of the caller that creates the statement will be logged when a statement leak is detected. If statement leak tracing is enabled, you can use the Administration Console to enable monitoring of the JDBC connection pool to get statistics on the number of statement leaks. The default value is 0, which disables statement leak tracing.

The following limitations apply to the statement leak timeout value:

- The value must be less than the value set for the connection `leak-timeout`.
- The value must be greater than the value set for `statement-timeout`.

**--statementleakreclaim**

Specifies whether leaked statements are reclaimed after the statements leak. Possible values are as follows:

**false**

Leaked statements are not reclaimed (default).

**true**

Leaked statements are reclaimed.

**--creationretryattempts**

Specifies the maximum number of times that Eclipse GlassFish retries to create a connection if the initial attempt fails. The default value is 0, which specifies that Eclipse GlassFish does not retry to create the connection.

**--creationretryinterval**

Specifies the interval, in seconds, between successive attempts to create a connection.

If `--creationretryattempts` is 0, the `--creationretryinterval` option is ignored. The default value is 10.

**--sqltracelisteners**

A list of one or more custom modules that provide custom logging of database activities. Each module must implement the `org.glassfish.api.jdbc.SQLTraceListener` public interface. When set to an appropriate value, SQL statements executed by applications are traced. This option has no default value.

**--statementtimeout**

Specifies the length of time in seconds after which a query that is not completed is terminated.

A query that remains incomplete for a long period of time might cause the application that

submitted the query to hang. To prevent this occurrence, use this option set a timeout for all statements that will be created from the connection pool that you are creating. When creating a statement, Eclipse GlassFish sets the `QueryTimeout` property on the statement to the length of time that is specified. The default value is -1, which specifies that incomplete queries are never terminated.

#### --lazyconnectionenlistment

Specifies whether a resource to a transaction is enlisted only when a method actually uses the resource. Possible values are as follows:

##### false

Resources to a transaction are always enlisted and not only when a method actually uses the resource (default).

##### true

Resources to a transaction are enlisted only when a method actually uses the resource.

#### --lazyconnectionassociation

Specifies whether a physical connection should be associated with the logical connection only when the physical connection is used, and disassociated when the transaction is completed. Such association and dissociation enable the reuse of physical connections. Possible values are as follows:

##### false

A physical connection is associated with the logical connection even before the physical connection is used, and is not disassociated when the transaction is completed (default).

##### true

A physical connection is associated with the logical connection only when the physical connection is used, and disassociated when the transaction is completed. The `--lazyconnectionenlistment` option must also be set to `true`.

#### --associatewiththread

Specifies whether a connection is associated with the thread to enable the thread to reuse the connection. If a connection is not associated with the thread, the thread must obtain a connection from the pool each time that the thread requires a connection. Possible values are as follows:

##### false

A connection is not associated with the thread (default).

##### true

A connection is associated with the thread.

#### --driverclassname

The name of the vendor-supplied JDBC driver class. This driver should implement the `java.sql.Driver` interface.

**--matchconnections**

Specifies whether a connection that is selected from the pool should be matched by the resource adaptor. If all the connections in the pool are homogenous, a connection picked from the pool need not be matched by the resource adapter, which means that this option can be set to false. Possible values are as follows:

**false**

A connection should not be matched by the resource adaptor (default).

**true**

A connection should be matched by the resource adaptor.

**--maxconnectionusagecount**

Specifies the maximum number of times that a connection can be reused. When this limit is reached, the connection is closed. By limiting the maximum number of times that a connection can be reused, you can avoid statement leaks.

The default value is 0, which specifies no limit on the number of times that a connection can be reused.

**--ping**

Specifies if the pool is pinged during pool creation or reconfiguration to identify and warn of any erroneous values for its attributes. Default value is false.

**--pooling**

Specifies if connection pooling is enabled for the pool. The default value is true.

**--statementcachefilesize**

The number of SQL statements to be cached using the default caching mechanism (Least Recently Used). The default value is 0, which indicates that statement caching is not enabled.

**--validationclassname**

The name of the class that provides custom validation when the value of `validationmethod` is `custom-validation`. This class must implement the `org.glassfish.api.jdbc.ConnectionValidation` interface, and it must be accessible to Eclipse GlassFish. This option is mandatory if the connection validation type is set to custom validation.

**--wrapjdbcobjects**

Specifies whether the pooling infrastructure provides wrapped JDBC objects to applications. By providing wrapped JDBC objects, the pooling infrastructure prevents connection leaks by ensuring that applications use logical connections from the connection pool, not physical connections. The use of logical connections ensures that the connections are returned to the connection pool when they are closed. However, the provision of wrapped JDBC objects can impair the performance of applications. The default value is true.

The pooling infrastructure provides wrapped objects for implementations of the following interfaces in the JDBC API:

- `java.sql.CallableStatement`
- `java.sql.DatabaseMetaData`
- `java.sql.PreparedStatement`
- `java.sql.ResultSet`
- `java.sql.Statement`

Possible values of `--wrapJdbcObjects` are as follows:

**false**

The pooling infrastructure does not provide wrapped JDBC objects to applications. (default).

**true**

The pooling infrastructure provides wrapped JDBC objects to applications.

**--description**

Text providing details about the specified JDBC connection pool.

**--property**

Optional attribute name/value pairs for configuring the pool. The following properties are available:

**user**

Specifies the user name for connecting to the database.

**password**

Specifies the password for connecting to the database.

**databaseName**

Specifies the database for this connection pool.

**serverName**

Specifies the database server for this connection pool.

**port**

Specifies the port on which the database server listens for requests.

**networkProtocol**

Specifies the communication protocol.

**roleName**

Specifies the initial SQL role name.

**datasourceName**

Specifies an underlying `XADatasource`, or a `ConnectionPoolDataSource` if connection pooling is

done.

#### **description**

Specifies a text description.

#### **url**

Specifies the URL for this connection pool. Although this is not a standard property, it is commonly used.

#### **dynamic-reconfiguration-wait-timeout-in-seconds**

Used to enable dynamic reconfiguration of the connection pool transparently to the applications that are using the pool, so that applications need not be re-enabled for the attribute or property changes to the pool to take effect. Any in-flight transaction's connection requests will be allowed to complete with the old pool configuration as long as the connection requests are within the timeout period, so as to complete the transaction. New connection requests will wait for the pool reconfiguration to complete and connections will be acquired using the modified pool configuration.

#### **LazyConnectionEnlistment**

Deprecated. Use the equivalent attribute. The default value is false.

#### **LazyConnectionAssociation**

Deprecated. Use the equivalent attribute. The default value is false.

#### **AssociateWithThread**

Deprecated. Use the equivalent attribute. The default value is false.

#### **MatchConnections**

Deprecated. Use the equivalent attribute. The default value is true.

#### **Prefer-Validate-Over-Recreate**

Specifies whether pool resizer should validate idle connections before destroying and recreating them. The default value is true.

#### **time-to-keep-queries-in-minutes**

Specifies the number of minutes that will be cached for use in calculating frequently used queries. Takes effect when SQL tracing and monitoring are enabled for the JDBC connection pool. The default value is 5 minutes.

#### **number-of-top-queries-to-report**

Specifies the number of queries to list when reporting the top and most frequently used queries. Takes effect when SQL tracing and monitoring are enabled for the JDBC connection pool. The default value is 10 queries.



If an attribute name or attribute value contains a colon, the backslash (\) must be used to escape the colon in the name or value. Other characters might also require an escape character. For more information about escape characters in command options, see the [asadmin\(1M\)](#) man page.

#### --target

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

### connectionpoolid

The name of the JDBC connection pool to be created.

## Examples

### Example 1 Creating a JDBC Connection Pool

This example creates a JDBC connection pool named `sample_derby_pool`.

```
asadmin> create-jdbc-connection-pool
--datasourceclassname org.apache.derby.jdbc.ClientDataSource
--restype javax.sql.XADatasource
--property portNumber=1527:password=APP:user=APP:serverName=
localhost:databaseName=sun-appserv-samples:connectionAttributes=\;
create\\=true sample_derby_pool
Command create-jdbc-connection-pool executed successfully
```

The escape character backslash (\) is used in the `--property` option to distinguish the semicolon (;). Two backslashes (\\\) are used to distinguish the equal sign (=).

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-jdbc-connection-pool\(1\)](#), [list-jdbc-connection-pools\(1\)](#)

# create-jdbc-resource

Creates a JDBC resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] create-jdbc-resource [--help]
--connectionpoolid connectionpoolid
[--enabled={false|true}]
[--description description]
[--property (property=value)[ :name=value]*]
[--target target]
jndi_name
```

## Description

The `create-jdbc-resource` subcommand creates a new JDBC resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

`-?`

Displays the help text for the subcommand.

#### --connectionpoolid

The name of the JDBC connection pool. If two or more JDBC resource elements point to the same connection pool element, they use the same pool connection at runtime.

#### --enabled

Determines whether the JDBC resource is enabled at runtime. The default value is true.

#### --description

Text providing descriptive details about the JDBC resource.

#### --property

Optional attribute name/value pairs for configuring the resource.

**--target**

This option helps specify the target to which you are deploying. Valid values are:

**server**

Deploys the component to the default server instance. This is the default value.

**domain**

Deploys the component to the domain.

**cluster\_name**

Deploys the component to every server instance in the cluster.

**instance\_name**

Deploys the component to a particular server instance.

The resource is always created for the domain as a whole, but the [resource-ref](#) for the resource is only created for the specified [--target](#). This means that although the resource is defined at the domain level, it is only available at the specified target level. Use the [create-resource-ref](#) subcommand to refer to the resource in multiple targets if needed.



## Operands

**jndi\_name**

The JNDI name of this JDBC resource.

## Examples

### Example 1 Creating a JDBC Resource

This example creates a JDBC resource named [jdbc/DerbyPool](#).

```
asadmin> create-jdbc-resource  
--connectionpoolid sample_derby_pool jdbc/DerbyPool  
Command create-jdbc-resource executed successfully.
```

## Exit Status

0

subcommand executed successfully

---

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-resource-ref\(1\)](#), [delete-jdbc-resource\(1\)](#), [list-jdbc-resources\(1\)](#)

# create-jmsdest

Creates a JMS physical destination

## Synopsis

```
asadmin [asadmin-options] create-jmsdest [--help]
--desttype dest_type
[--property (name=value)[:name=value]*]
[--target target]
[--force={false|true}]
dest_name
```

## Description

The `create-jmsdest` subcommand creates a Java Message Service (JMS) physical destination. Typically, you use the `create-jms-resource` subcommand to create a JMS destination resource that has a `Name` property that specifies the physical destination. The physical destination is created automatically when you run an application that uses the destination resource. Use the `create-jmsdest` subcommand if you want to create a physical destination with non-default property settings.

This subcommand is supported in remote mode only. Remote `asadmin` subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --desttype

The type of the JMS destination. Valid values are `topic` and `queue`.

### --property

Optional attribute name/value pairs for configuring the physical destination. You can specify the following properties for a physical destination.

#### MaxNumMsgs

The maximum number of unconsumed messages permitted for the destination. A value of -1

denotes an unlimited number of messages. The default value is -1. For the dead message queue, the default value is 1000.

If the `limitBehavior` property is set to `FLOW_CONTROL`, it is possible for the specified message limit to be exceeded because the broker cannot react quickly enough to stop the flow of incoming messages. In such cases, the value specified for `maxNumMsgs` serves as merely a hint for the broker rather than a strictly enforced limit.

### **MaxBytesPerMsg**

The maximum size, in bytes, of any single message. Rejection of a persistent message is reported to the producing client with an exception; no notification is sent for non-persistent messages. The value may be expressed in bytes, kilobytes, or megabytes, using the following suffixes:

**b**

Bytes

**k**

Kilobytes (1024 bytes)

**m**

Megabytes (1024 x 1024 = 1,048,576 bytes)

A value with no suffix is expressed in bytes; a value of -1 denotes an unlimited message size. The default value is -1.

### **MaxTotalMsgBytes**

The maximum total memory, in bytes, for unconsumed messages. The default value is -1. The syntax is the same as for `maxBytesPerMsg`. For the dead message queue, the default value is `10m`.

### **LimitBehavior**

The behavior of the message queue broker when the memory-limit threshold is reached. Valid values are as follows:

#### **REJECT\_NEWEST**

Reject newest messages and notify the producing client with an exception only if the message is persistent. This is the default value.

#### **FLOW\_CONTROL**

Slow the rate at which message producers send messages.

#### **REMOVE\_OLDEST**

Throw out the oldest messages.

#### **REMOVE\_LOW\_PRIORITY**

Throw out the lowest-priority messages according to age, with no notification to the producing client.

If the value is `REMOVE_ODEST` or `REMOVE_LOW_PRIORITY` and the `useDMQ` property is set to `true`, excess messages are moved to the dead message queue. For the dead message queue itself, the default limit behavior is `REMOVE_ODEST`, and the value cannot be set to `FLOW_CONTROL`.

#### MaxNumProducers

The maximum number of message producers for the destination. When this limit is reached, no new producers can be created. A value of -1 denotes an unlimited number of producers. The default value is 100. This property does not apply to the dead message queue.

#### ConsumerFlowLimit

The maximum number of messages that can be delivered to a consumer in a single batch. A value of -1 denotes an unlimited number of messages. The default value is 1000. The client runtime can override this limit by specifying a lower value on the connection factory object. In load-balanced queue delivery, this is the initial number of queued messages routed to active consumers before load balancing begins.

#### UseDMQ

If set to `true`, dead messages go to the dead message queue. If set to `false`, dead messages are discarded. The default value is `true`.

#### ValidateXMLSchemaEnabled

If set to `true`, XML schema validation is enabled for the destination. The default value is `false`. When XML validation is enabled, the Message Queue client runtime will attempt to validate an XML message against the specified XSDs (or against the DTD, if no XSD is specified) before sending it to the broker. If the specified schema cannot be located or the message cannot be validated, the message is not sent, and an exception is thrown. This property should be set when a destination is inactive: that is, when it has no consumers or producers and when there are no messages in the destination. Otherwise the producer must reconnect.

#### XMLSchemaURIList

A space-separated list of XML schema document (XSD) URI strings. The URIs point to the location of one or more XSDs to use for XML schema validation, if `validateXMLSchemaEnabled` is set to `true`. The default value is `null`.

Use double quotes around this value if multiple URIs are specified, as in the following example:

```
"http://foo/flap.xsd http://test.com/test.xsd"
```

If this property is not set or `null` and XML validation is enabled, XML validation is performed using a DTD specified in the XML document. If an XSD is changed as a result of changing application requirements, all client applications that produce XML messages based on the changed XSD must reconnect to the broker.

To modify the value of these properties, you can use the `as-install/mq/bin/imqcmd` command. See

"[Physical Destination Property Reference](#)" in Open Message Queue Administration Guide for more information.

#### --target

Creates the physical destination only for the specified target. Although the `create-jmsdest` subcommand is related to resources, a physical destination is created using the JMS Service (JMS Broker), which is part of the configuration. A JMS Broker is configured in the config section of `domain.xml`. Valid values are as follows:

##### **server**

Creates the physical destination for the default server instance. This is the default value.

##### **configuration-name**

Creates the physical destination in the specified configuration.

##### **cluster-name**

Creates the physical destination for every server instance in the specified cluster.

##### **instance-name**

Creates the physical destination for the specified server instance.

#### --force

Specifies whether the subcommand overwrites the existing JMS physical destination of the same name. The default value is `false`.

## Operands

### **dest\_name**

A unique identifier for the JMS destination to be created.

## Examples

### Example 1 Creating a JMS physical destination

The following subcommand creates a JMS physical queue named `PhysicalQueue` with non-default property values.

```
asadmin> create-jmsdest --desttype queue
--property maxNumMsgs=1000:maxBytesPerMsg=5k PhysicalQueue
Command create-jmsdest executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jms-resource\(1\)](#), [delete-jmsdest\(1\)](#), [flush-jmsdest\(1\)](#), [list-jmsdest\(1\)](#)

# create-jms-host

Creates a JMS host

## Synopsis

```
asadmin [asadmin-options] create-jms-host [--help]
--mqhost mq-host --mqport mq-port
--mquser mq-user --mqpassword mq-password
[--target target]
[--force={false|true}]
jms_host_name
```

## Description

Creates a Java Message Service (JMS) host within the JMS service.

This subcommand is supported in remote mode only. Remote `asadmin` subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --mqhost

The host name for the JMS service.

#### --mqport

The port number used by the JMS service.

#### --mquser

The user name for the JMS service.

#### --mqpassword

The password for the JMS service.

**--target**

Creates the JMS host only for the specified target. Valid values are as follows:

**server**

Creates the JMS host for the default server instance. This is the default value.

**configuration-name**

Creates the JMS host in the specified configuration.

**cluster-name**

Creates the JMS host for every server instance in the specified cluster.

**instance-name**

Creates the JMS host for the specified server instance.

**--force**

Specifies whether the subcommand overwrites the existing JMS host of the same name. The default value is **false**.

## Operands

**jms\_host\_name**

A unique identifier for the JMS host to be created.

## Examples

### Example 1 Creating a JMS host using a non-default port

The following command creates a JMS host named **MyNewHost** on the system **pigeon**.

```
asadmin> create-jms-host --mqhost pigeon.example.com --mqport 7677  
--mquser admin --mqpassword admin MyNewHost  
Jms Host MyNewHost created.  
Command create-jms-host executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

---

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-jms-host\(1\)](#), [jms-ping\(1\)](#), [list-jms-hosts\(1\)](#)

# create-jms-resource

Creates a JMS resource

## Synopsis

```
asadmin [asadmin-options] create-jms-resource [--help]
--restype type
[--target target]
[--enabled={true|false}]
[--description text]
[--property (name=value)[:name=value]*]
[--force={false|true}]
jndi_name
```

## Description

The `create-jms-resource` subcommand creates a Java Message Service (JMS) connection factory resource or a JMS destination resource.

This subcommand is supported in remote mode only. Remote `asadmin` subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --restype

The JMS resource type, which can be `jakarta.jms.Topic`, `jakarta.jms.Queue`, `jakarta.jms.ConnectionFactory`, `jakarta.jms.TopicConnectionFactory`, or `jakarta.jms.QueueConnectionFactory`.

#### --target

Creates the JMS resource only for the specified target. Valid values are as follows:



The resource is always created for the domain as a whole, but the <resource-ref> element for the resource is only created for the specified --target. This means that although the resource is defined at the domain level, it is only active at the specified --target.

#### **server**

Creates the JMS resource for the default server instance. This is the default value.

#### **domain**

Creates the JMS resource for the domain.

#### **cluster-name**

Creates the JMS resource for every server instance in the specified cluster.

#### **instance-name**

Creates the JMS resource for the specified server instance.

#### **--enabled**

If set to true (the default), the resource is enabled at runtime.

#### **--description**

Text providing details about the JMS resource.

#### **--property**

Optional attribute name/value pairs for configuring the JMS resource.

You can specify the following properties for a connection factory resource:

#### **ClientId**

A client ID for a connection factory that will be used by a durable subscriber.

#### **AddressList**

A comma-separated list of message queue addresses that specify the host names (and, optionally, port numbers) of a message broker instance or instances with which your application will communicate. For example, the value could be `earth` or `earth:7677`. Specify the port number if the message broker is running on a port other than the default (7676). The default value is an address list composed from the JMS hosts defined in the server's JMS service configuration. The default value is `localhost` and the default port number is 7676. The client will attempt a connection to a broker on port 7676 of the local host.

#### **UserName**

The user name for the connection factory. The default value is `guest`.

#### **Password**

The password for the connection factory. The default value is `guest`.

### ReconnectEnabled

A value of `true` indicates that the client runtime attempts to reconnect to a message server (or the list of addresses in the `AddressList`) when a connection is lost. The default value is `false`.

### ReconnectAttempts

The number of attempts to connect (or reconnect) for each address in the `AddressList` before the client runtime tries the next address in the list. A value of -1 indicates that the number of reconnect attempts is unlimited (the client runtime attempts to connect to the first address until it succeeds). The default value is 6.

### ReconnectInterval

The interval in milliseconds between reconnect attempts. This applies to attempts on each address in the `AddressList` and for successive addresses in the list. If the interval is too short, the broker does not have time to recover. If it is too long, the reconnect might represent an unacceptable delay. The default value is 30,000 milliseconds.

### AddressListBehavior

Specifies whether connection attempts are in the order of addresses in the `AddressList (PRIORITY)` or in a random order (`RANDOM`). `PRIORITY` means that the reconnect will always try to connect to the first server address in the `AddressList` and will use another one only if the first broker is not available. If you have many clients attempting a connection using the same connection factory, specify `RANDOM` to prevent them from all being connected to the same address. The default value is the `AddressListBehavior` value of the server's JMS service configuration.

### AddressListIterations

The number of times the client runtime iterates through the `AddressList` in an effort to establish (or re-establish) a connection). A value of -1 indicates that the number of attempts is unlimited. The default value is -1.

Additionally, you can specify `connector-connection-pool` attributes as connector resource properties. For a list of these attributes, see "["connector-connection-pool"](#)" in Eclipse GlassFish Application Deployment Guide.

You can specify the following properties for a destination resource:

#### Name

The name of the physical destination to which the resource will refer. The physical destination is created automatically when you run an application that uses the destination resource. You can also create a physical destination with the `create-jmsdest` subcommand. If you do not specify this property, the JMS service creates a physical destination with the same name as the destination resource (replacing any forward slash in the JNDI name with an underscore).

#### Description

A description of the physical destination.

**--force**

Specifies whether the subcommand overwrites the existing JMS resource of the same name. The default value is `false`.

# Operands

**jndi\_name**

The JNDI name of the JMS resource to be created.

## Examples

### Example 1 Creating a JMS connection factory resource for durable

subscriptions

The following subcommand creates a connection factory resource of type `jakarta.jms.ConnectionFactory` whose JNDI name is `jms/DurableConnectionFactory`. The `ClientId` property sets a client ID on the connection factory so that it can be used for durable subscriptions. The JNDI name for a JMS resource customarily includes the `jms/` naming subcontext.

```
asadmin> create-jms-resource --restype jakarta.jms.ConnectionFactory
--description "connection factory for durable subscriptions"
--property ClientId=MyID jms/DurableConnectionFactory
Connector resource jms/DurableConnectionFactory created.
Command create-jms-resource executed successfully.
```

### Example 2 Creating a JMS destination resource

The following subcommand creates a destination resource whose JNDI name is `jms/MyQueue`. The `Name` property specifies the physical destination to which the resource refers.

```
asadmin> create-jms-resource --restype jakarta.jms.Queue
--property Name=PhysicalQueue jms/MyQueue
Administered object jms/MyQueue created.
Command create-jms-resource executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-jms-resource\(1\)](#), [list-jms-resources\(1\)](#)

# create-jndi-resource

Registers a JNDI resource

## Synopsis

```
asadmin [asadmin-options] create-jndi-resource [--help]
[--target target]
--restype restype --factoryclass factoryclass
--jndilookupname jndilookupname [--enabled={true|false}]
[--description description]
[--property (name=value)[:name=value]*]
jndi-name
```

## Description

The **create-jndi-resource** subcommand registers a JNDI resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

This option specifies the target for which you are registering a JNDI resource. Valid values for target are described below.



The resource is always created for the domain as a whole, but the **resource-ref** for the resource is only created for the specified **--target**. This means that although the resource is defined at the domain level, it is only available at the specified target level. Use the **create-resource-ref** subcommand to refer to the resource in multiple targets if needed.

#### server

Creates the resource for the default server instance. This value is the default.

**domain**

Creates the resource for the domain

**cluster-name**

Creates the resource for every server instance in the cluster

**instance-name**

Creates the resource for a particular server instance

**--restype**

The JNDI resource type. Valid values are `topic` or `queue`.

**--factoryclass**

The class that creates the JNDI resource.

**--jndilookupname**

The lookup name that the external container uses.

**--enabled**

Determines whether the resource is enabled at runtime. Default is true.

**--description**

The text that provides details about the JNDI resource.

**--property**

Optional properties for configuring the resource. Each property is specified as a name-value pair. The available properties are specific to the implementation that is specified by the `--factoryclass` option and are used by that implementation. Eclipse GlassFish itself does not define any properties for configuring a JNDI resource.

## Operands

**jndi-name**

The unique name of the JNDI resource to be created.

## Examples

### Example 1 Creating a JNDI Resource

This example creates the JNDI resource `my-jndi-resource` for the default server instance.

```
asadmin> create-jndi-resource  
--restype com.example.jndi.MyResourceType  
--factoryclass com.example.jndi.MyInitialContextFactoryClass  
--jndilookupname remote-jndi-name  
--description "sample JNDI resource" my-jndi-resource  
JNDI resource my-jndi-resource created.  
Command create-jndi-resource executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-resource-ref\(1\)](#), [delete-jndi-resource\(1\)](#), [list-jndi-resources\(1\)](#)

# create-jvm-options

Creates options for the Java application launcher

## Synopsis

```
asadmin [asadmin-options] create-jvm-options [--help]
[--target target] [--profiler={true|false}]
(jvm-option-name=jvm-option-value) [:jvm-option-name=jvm-option-value*]
```

## Description

The `create-jvm-options` subcommand creates command-line options that are passed to the Java application launcher when Eclipse GlassFish is started. The options that this subcommand creates are in addition to the options that are preset with Eclipse GlassFish. Java application launcher options are stored in the Java configuration `java—config` element or the profiler `profiler` element of the `domain.xml` file. The options are sent to the command line in the order they appear in the `java—config` element or the profiler `profiler` element in the `domain.xml` file.

Profiler options are used to record the settings that are required to start a particular profiler. The profiler must already exist. If necessary, use the `create-profiler(1)` subcommand to create the profiler.

This subcommand can be used to create the following types of options:

- Java system properties. These options are set through the `-D` option of the Java application launcher. For example:

`-Djava.security.manager`  
`-Denvironment=Production`

- Startup parameters for the Java application launcher. These options are preceded by the dash character (`-`). For example:

`--XX:PermSize=size`  
`-Xmx1024m`  
`-d64`

If the subcommand specifies an option that already exists, the command does not re-create the option.



Ensure that any option that you create is valid. The subcommand might allow you to create an invalid option, but such an invalid option can cause startup to fail.

An option can be verified by examining the server log after Eclipse GlassFish starts. Options for the Java application launcher are written to the `server.log` file before any other information when Eclipse GlassFish starts.

The addition of some options requires a server restart for changes to become effective. Other options are set immediately in the environment of the domain administration server (DAS) and do not require a restart. Whether a restart is required depends on the type of option.

- Restart is not required for Java system properties whose names do not start with `-Djava.` or `-Djavax.` (including the trailing period). For example, restart is not required for the following Java system property:

`-Denvironment=Production`

- Restart is required for the following options:

- Java system properties whose names start with `-Djava.` or `-Djavax.` (including the trailing period). For example:

`-Djava.security.manager`

- Startup parameters for the Java application launcher. For example:

`-client`

`-Xmx1024m`

`-d64`

To restart the DAS, use the `restart-domain(1)` command.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--target`

Specifies the target on which you are creating Java application launcher options.

Valid values are as follows:

`server`

Specifies the DAS (default).

**instance-name**

Specifies a Eclipse GlassFish instance.

**cluster-name**

Specifies a cluster.

**configuration-name**

Specifies a named configuration.

**--profiler**

Indicates whether the Java application launcher options are for the profiler. The profiler must exist for this option to be true. Default is false.

# Operands

**jvm-option-name**

One or more options delimited by a colon (:). The format of an option depends on the following:

- If the option has a name and a value, the format is option-name=value.
- If the option has only a name, the format is option-name. For example, `-Xmx2048m`.
- If the first option name could be misinterpreted as one or more `asadmin` short options, the format is -- option-name. For example, `-server` in the following command could be misinterpreted as `-se`, the `asadmin` short forms for `--secure` and `--echo`:

```
create-jvm-options -server
```

To create the JVM option `-server`, instead use the command:

```
create-jvm-options -- -server
```



If an option name or option value contains a colon, the backslash (\) must be used to escape the colon in the name or value. Other characters might also require an escape character. For more information about escape characters in subcommand options, see the `asadmin(1M)` man page.

# Examples

## Example 1 Setting Java System Properties

This example sets multiple Java system properties.

```
asadmin> create-jvm-options -Dunixlocation=/root/example:  
-Dvariable=\$HOME:-Dwindowslocation=d:\\sun\\appserver:-Doption1=-value1  
created 4 option(s)  
Command create-jvm-options executed successfully.
```

## Example 2 Setting a Startup Parameter for the Java Application

Launcher

This example sets the maximum available heap size to 1024.

```
asadmin> create-jvm-options -Xmx1024m  
created 1 option(s)  
Command create-jvm-options executed successfully.
```

## Example 3 Setting Multiple Startup Parameters for the Java Application

Launcher

This example sets the maximum available heap size to 1024 and requests details about garbage collection.

```
asadmin> create-jvm-options "-Xmx1024m:-XX:+PrintGCDetails"  
created 1 option(s)  
Command create-jvm-options executed successfully.
```

In this case, one of the two parameters already exists, so the subcommand reports that only one option was set.

## Example 4 Setting a JVM Startup Parameter for the Profiler

This example sets a JVM startup parameter for the profiler.

```
asadmin> create-jvm-options --profiler=true -XX\:MaxPermSize=192m
created 1 option(s)
Command create-jvm-options executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-profiler\(1\)](#), [delete-jvm-options\(1\)](#), [list-jvm-options\(1\)](#), [restart-domain\(1\)](#)

For more information about the Java application launcher, see the reference page for the operating system that you are using:

- Oracle Solaris and Linux: java - the Java application launcher (<http://docs.oracle.com/javase/6/docs/technotes/tools/solaris/java.html>)
- Windows: java - the Java application launcher (<http://docs.oracle.com/javase/6/docs/technotes/tools/windows/java.html>)

# create-lifecycle-module

Creates a lifecycle module

## Synopsis

```
asadmin [asadmin-options] create-lifecycle-module [--help]
--classname classname
[--enabled={true|false}] [--target target]
[--classpath classpath] [--loadorder loadorder]
[--failurefatal={false|true} ] [--description description]
[--property (name=value)[:name=value]*]
module_name
```

## Description

The `create-lifecycle-module` subcommand creates a lifecycle module. A lifecycle module provides a means of running a short or long duration Java-based task at a specific stage in the server life cycle. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --classname

This is the fully qualified name of the startup class.

#### --target

Indicates the location where the lifecycle module is to be created. Valid values are

- `server`- Specifies the default server instance as the target for creating the lifecycle module. `server` is the name of the default server instance and is the default value for this option.
- `cluster_name`- Specifies a particular cluster as the target for creating the lifecycle module.
- `instance_name`- Specifies a particular stand-alone server instance as the target for creating the lifecycle module.

**--classpath**

This option indicates where the lifecycle module is located. It is a classpath with the standard format: either colon-separated (Unix) or semicolon-separated (Windows) JAR files and directories. The referenced JAR files and directories are not uploaded to the server instance.

**--loadorder**

This option represents an integer value that can be used to force the order in which deployed lifecycle modules are loaded at server startup. Smaller numbered modules are loaded sooner. Order is unspecified if two or more lifecycle modules have the same load-order value. The default is `Integer.MAX_VALUE`, which means the lifecycle module is loaded last.

**--failurefatal**

This option tells the system what to do if the lifecycle module does not load correctly. When this option is set to true, the system aborts the server startup if this module does not load properly. The default value is false.

**--enabled**

This option determines whether the lifecycle module is enabled at runtime. The default value is true.

**--description**

This is the text description of the lifecycle module.

**--property**

This is an optional attribute containing name/value pairs used to configure the lifecycle module.

## Operands

**module\_name**

This operand is a unique identifier for the deployed server lifecycle event listener module.

## Examples

### Example 1 Creating a Lifecycle Module

The following example creates a lifecycle module named `customSetup`.

```
asadmin> create-lifecycle-module --classname "com.acme.CustomSetup"
--classpath "/export/customSetup" --loadorder 1 --failurefatal=true
--description "this is a sample customSetup"
--property rmi="Server\=acme1\:7070":timeout=30 customSetup
Command create-lifecycle-module executed successfully
```

The escape character \ is used in the property option to specify that the equal sign (=) and colon (:) are part of the `rmi` property value.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[delete-lifecycle-module\(1\)](#), [list-lifecycle-modules\(1\)](#)

"Developing Lifecycle Listeners" in Eclipse GlassFish Application Development Guide

# create-local-instance

Creates a Eclipse GlassFish instance on the host where the subcommand is run

## Synopsis

```
asadmin [asadmin-options] create-local-instance [--help]
[--node node-name] [--nodedir node-dir]
[--config config-name | --cluster cluster-name]
[--lbenabled={true|false}]
[--portbase port-number] [--checkports={true|false}]
[--savemasterpassword={false|true}]
[--usemasterpassword={false|true}]
[--systemproperties (name=value)[:name=value]* ]
instance-name
```

## Description

The `create-local-instance` subcommand creates a Eclipse GlassFish instance on the node that represents the host where the subcommand is run. This subcommand does not require the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured.

You must run this subcommand from the host that is represented by the node where the instance is to reside. To contact the domain administration server (DAS), this subcommand requires the name of the host where the DAS is running. If a nondefault port is used for administration, this subcommand also requires the port number. If you are adding the first instance to a node, you must provide this information through the `--host` option and the `--port` option of the [asadmin\(1M\)](#) utility. For the second and later instances, this information is obtained from the DAS properties of the node.

A Eclipse GlassFish instance is a single Virtual Machine for the Java platform (Java Virtual Machine or JVM machine) on a single node in which Eclipse GlassFish is running. A node defines the host where the Eclipse GlassFish instance resides. The JVM machine must be compatible with the Java Platform, Enterprise Edition (Jakarta EE).

A Eclipse GlassFish instance requires a reference to the following items:

- The node that defines the host where the instance resides. The node can be specified in the command to create the instance, but is required only if more than one node exists in the directory where files for nodes are stored. If no node is specified, the behavior of the subcommand depends on the number of existing nodes in the directory where nodes are stored:
  - If no nodes exist, the subcommand creates a node for the instance. The name of the node is the name of the host on which the subcommand is run.
  - If only one node exists, the subcommand creates a reference to the existing node for the

- instance.
- If two or more nodes exist, an error occurs.
  - The named configuration that defines the configuration of the instance. The configuration can be specified in the command to create the instance, but is not required. If no configuration is specified for an instance that is not joining a cluster, the subcommand creates a configuration for the instance. An instance that is joining a cluster receives its configuration from its parent cluster.

Each Eclipse GlassFish instance is one of the following types of instance:

### **Standalone instance**

A standalone instance does not share its configuration with any other instances or clusters. A standalone instance is created if either of the following conditions is met:

- No configuration or cluster is specified in the command to create the instance.
- A configuration that is not referenced by any other instances or clusters is specified in the command to create the instance.

When no configuration or cluster is specified, a copy of the [default-config](#) configuration is created for the instance. The name of this configuration is `instance-name`-config``, where `instance-name` represents the name of an unclustered server instance.

### **Shared instance**

A shared instance shares its configuration with other instances or clusters. A shared instance is created if a configuration that is referenced by other instances or clusters is specified in the command to create the instance.

### **Clustered instance**

A clustered instance inherits its configuration from the cluster to which the instance belongs and shares its configuration with other instances in the cluster. A clustered instance is created if a cluster is specified in the command to create the instance.

Any instance that is not part of a cluster is considered an unclustered server instance. Therefore, standalone instances and shared instances are unclustered server instances.

By default, this subcommand attempts to resolve possible port conflicts for the instance that is being created. The subcommand also assigns ports that are currently not in use and not already assigned to other instances on the same node. The subcommand assigns these ports on the basis of an algorithm that is internal to the subcommand. Use the [--systemproperties](#) option to resolve port conflicts for additional instances on the same node. System properties of an instance can be manipulated by using the [create-system-properties\(1\)](#) subcommand and the [delete-system-property\(1\)](#) subcommand.

When creating an instance, the subcommand retrieves the files that are required for secure synchronization with the domain administration server (DAS). The instance is synchronized with the DAS when the instance is started.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

-?

Displays the help text for the subcommand.

### --node

The name of the node that defines the host where the instance is to be created. The node must be specified only if more than one node exists in the directory where nodes are stored. Otherwise, the node may be omitted. If a node is specified, the node must exist.

If no node is specified, the behavior of the subcommand depends on the number of existing nodes in the directory where nodes are stored:

- If no nodes exist, the subcommand creates a node for the instance. The name of the node is the name of the host on which the subcommand is run.
- If only one node exists, the subcommand creates a reference to the existing node for the instance.
- If two or more nodes exist, an error occurs.

### --nodedir

The path to the directory in which the files for instance's node is to be stored. The default is `as-install/nodes`.

### --config

Specifies the named configuration that the instance references. The configuration must exist and must not be named `default-config` or `server-config`. Specifying the `--config` option creates a shared instance.

The `--config` option and the `--cluster` option are mutually exclusive. If both options are omitted, a standalone instance is created.

### --cluster

Specifies the cluster from which the instance inherits its configuration. Specifying the `--cluster` option creates a clustered instance.

The `--config` option and the `--cluster` option are mutually exclusive. If both options are omitted, a standalone instance is created.

### --lbenabled

Specifies whether the instance is enabled for load balancing. Possible values are as follows:

#### true

The instance is enabled for load balancing (default).

When an instance is enabled for load balancing, a load balancer sends requests to the instance.

#### false

The instance is disabled for load balancing.

When an instance is disabled for load balancing, a load balancer does not send requests to the instance.

#### --portbase

Determines the number with which the port assignment should start. An instance uses a certain number of ports that are statically assigned. The portbase value determines where the assignment should start. The values for the ports are calculated as follows:

- Administration port: portbase + 48
- HTTP listener port: portbase + 80
- HTTPS listener port: portbase + 81
- JMS port: portbase + 76
- IIOP listener port: portbase + 37
- Secure IIOP listener port: portbase + 38
- Secure IIOP with mutual authentication port: portbase + 39
- JMX port: portbase + 86
- JPA debugger port: portbase + 9
- Felix shell service port for OSGi module management: portbase + 66

When the `--portbase` option is specified, the output of this subcommand includes a complete list of used ports.

#### --checkports

Specifies whether to check for the availability of the administration, HTTP, JMS, JMX, and IIOP ports. The default value is `true`.

#### --savemasterpassword

Setting this option to `true` allows the master password to be written to the file system. If the master password is written to the file system, the instance can be started without the need to prompt for the password. If this option is `true`, the `--usemasterpassword` option is also true, regardless of the value that is specified on the command line. Because writing the master password to the file system is an insecure practice, the default is `false`.

The master-password file for an instance is saved in the node directory, not the domain directory. Therefore, this option is required only for the first instance that is created for each node in a domain.

**--usemasterpassword**

Specifies whether the key store is encrypted with a master password that is built into the system or a user-defined master password.

If `false` (default), the keystore is encrypted with a well-known password that is built into the system. Encrypting the keystore with a password that is built into the system provides no additional security.

If `true`, the subcommand obtains the master password from the `AS_ADMIN_MASTERPASSWORD` entry in the password file or prompts for the master password. The password file is specified in the `--passwordfile` option of the `asadmin(1M)` utility.

If the `--savemasterpassword` option is `true`, this option is also true, regardless of the value that is specified on the command line.

The master password must be the same for all instances in a domain.

**--systemproperties**

Defines system properties for the instance. These properties override property definitions for port settings in the instance's configuration. Predefined port settings must be overridden if, for example, two clustered instances reside on the same host. In this situation, port settings for one instance must be overridden because both instances share the same configuration.

The following properties are available:

**ASADMIN\_LISTENER\_PORT**

This property specifies the port number of the HTTP port or HTTPS port through which the DAS connects to the instance to manage the instance. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**HTTP\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTP requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**HTTP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used to listen for HTTPS requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**IIOP\_LISTENER\_PORT**

This property specifies the port number of the port that is used for IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

**IIOP\_SSL\_LISTENER\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## **IIOP\_SSL\_MUTUALAUTH\_PORT**

This property specifies the port number of the port that is used for secure IIOP connections with client authentication. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## **JAVA\_DEBUGGER\_PORT**

This property specifies the port number of the port that is used for connections to the Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugger. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## **JMS\_PROVIDER\_PORT**

This property specifies the port number for the Java Message Service provider. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## **JMX\_SYSTEM\_CONNECTOR\_PORT**

This property specifies the port number on which the JMX connector listens. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

## **OSGI\_SHELL\_TELNET\_PORT**

This property specifies the port number of the port that is used for connections to the Apache Felix Remote Shell (<http://felix.apache.org/site/apache-felix-remote-shell.html>). This shell uses the Felix shell service to interact with the OSGi module management subsystem. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

# Operands

## **instance-name**

The name of the instance that is being created.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period
  - Underscore

- The name must be unique in the domain and must not be the name of another Eclipse GlassFish instance, a cluster, a named configuration, or a node.
- The name must not be `domain`, `server`, or any other keyword that is reserved by Eclipse GlassFish.

## Examples

### Example 1 Creating a Standalone Eclipse GlassFish Instance

This example creates the standalone instance `i13` on the host where the command is run. The DAS is running on the same host. The instance references the only existing node.

```
asadmin> create-local-instance i13
Rendezvoused with DAS on localhost:4848.
Port Assignments for server instance i13:
JMX_SYSTEM_CONNECTOR_PORT=28686
JMS_PROVIDER_PORT=27676
HTTP_LISTENER_PORT=28080
ASADMIN_LISTENER_PORT=24848
JAVA_DEBUGGER_PORT=29009
IIOP_SSL_LISTENER_PORT=23820
IIOP_LISTENER_PORT=23700
OSGI_SHELL_TELNET_PORT=26666
HTTP_SSL_LISTENER_PORT=28181
IIOP_SSL_MUTUALAUTH_PORT=23920
Command create-local-instance executed successfully.
```

### Example 2 Creating a Clustered Eclipse GlassFish Instance on a Specific Node

This example creates the clustered instance `yml12` on node `sj02`. The instance is a member of the cluster `ymlclust`.

The command is run on the host `sj02`, which is the host that the node `sj02` represents. The DAS is running on the host `sr04` and uses the default HTTP port for administration. Because no instances exist on the node, the host on which the DAS is running is provided through the `--host` option of the `asadmin` utility.

```
sj02# asadmin --host sr04 create-local-instance --cluster ymlclust --node sj02 yml12
Rendezvoused with DAS on sr04:4848.
Port Assignments for server instance yml12:
JMX_SYSTEM_CONNECTOR_PORT=28686
JMS_PROVIDER_PORT=27676
HTTP_LISTENER_PORT=28080
ASADMIN_LISTENER_PORT=24848
JAVA_DEBUGGER_PORT=29009
IIOP_SSL_LISTENER_PORT=23820
IIOP_LISTENER_PORT=23700
OSGI_SHELL_TELNET_PORT=26666
HTTP_SSL_LISTENER_PORT=28181
IIOP_SSL_MUTUALAUTH_PORT=23920
Command create-local-instance executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [create-system-properties\(1\)](#), [delete-local-instance\(1\)](#), [delete-system-property\(1\)](#), [list-instances\(1\)](#), [start-local-instance\(1\)](#), [stop-local-instance\(1\)](#)

# create-managed-executor-service

Creates a managed executor service resource

## Synopsis

```
asadmin [asadmin-options] create-managed-executor-service [--help]
[--enabled={false|true}]
[--contextinfoenabled={false|true}]
[--contextinfo={Classloader|JNDI|Security|WorkArea}]
[--threadpriority threadpriority]
[--longrunningtasks={false|true}]
[--hungafterseconds hungafterseconds]
[--hungloggerprintonce={false|true}]
[--hungloggerinitialdelayseconds hungloggerinitialdelayseconds]
[--hungloggerintervalseconds hungloggerintervalseconds]
[--corepoolsize corepoolsize]
[--maximumpoolsize maximumpoolsize]
[--keepaliveseconds keepaliveseconds]
[--threadlifetimeseconds threadlifetimeseconds]
[--taskqueuecapacity taskqueuecapacity]
[--description description]
[--property property]
[--target target]
jndi_name
```

## Description

The `create-managed-executor-service` subcommand creates a managed executor service resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--enabled**

Determines whether the resource is enabled at runtime. The default value is `true`.

**--contextinfoenabled**

Determines whether container contexts are propagated to threads. If set to `true`, the contexts specified in the `--contextinfo` option are propagated. If set to `false`, no contexts are propagated and the `--contextinfo` option is ignored. The default value is `true`.

**--contextinfo**

Specifies individual container contexts to propagate to threads. Valid values are Classloader, JNDI, Security, and WorkArea. Values are specified in a comma-separated list and are case-insensitive. All contexts are propagated by default.

**--threadpriority**

Specifies the priority to assign to created threads. The default value is 5.

**--longrunningtasks**

Specifies whether the resource should be used for long-running tasks. The default value is `false`. If set to `true`, long-running tasks are not reported as stuck.

**--hungafterseconds**

Specifies the number of seconds that a task can execute before it is considered unresponsive. The default value is 0, which means that tasks are never considered unresponsive.

**--hungloggerprintonce**

Specifies whether to print the warning message once or repeatedly. The default value is false. If set to true, the warning message is printed only once when detect a hung task exceeds "hungafterseconds".

**--hungloggerinitialdelayseconds**

Specifies the number of seconds to delay logging the detection of hung tasks. The default value is 60.

**--hungloggerintervalseconds**

Specifies the number of seconds between logging the detection of hung tasks. The default value is 60.

**--corepoolsize**

Specifies the number of threads to keep in a thread pool, even if they are idle. The default value is 0. When a new task is submitted and the number of running threads is less than `corepoolsize`, a new thread is created to handle the request. When the value for `corepoolsize` is 0 (the default), new threads are never created unless the task queue is full or the resource is using direct queuing. Direct queuing occurs when `taskqueuecapacity` is 0, or when `taskqueuecapacity` is 2147483647 and `corepoolsize` is 0.

**--maximumpoolsize**

Specifies the maximum number of threads that a thread pool can contain. The default value is 2147483647, which means that the thread pool is essentially unbounded and can contain any number of threads.

**--keepaliveseconds**

Specifies the number of seconds that threads can remain idle when the number of threads is greater than `corepoolsize`. The default value is 60.

**--threadlifetimeseconds**

Specifies the number of seconds that threads can remain in a thread pool before being purged, regardless of whether the number of threads is greater than `corepoolsize` or whether the threads are idle. The default value is 0, which means that threads are never purged.

**--taskqueuecapacity**

Specifies the number of submitted tasks that can be stored in the task queue awaiting execution. The default value is 2147483647, which means that the task queue is essentially unbounded and can store any number of submitted tasks.

**--description**

Descriptive details about the resource.

**--property**

Optional attribute name/value pairs for configuring the resource.

Eclipse GlassFish does not define any additional properties for this resource. Moreover, this resource does not currently use any additional properties.

**--target**

Specifies the target for which you are creating the resource. Valid targets are:

**server**

Creates the resource for the default server instance. This is the default value.

**domain**

Creates the resource for the domain.

**cluster\_name**

Creates the resource for every server instance in the specified cluster.

**instance\_name**

Creates the resource for the specified server instance.

# Operands

**jndi\_name**

The JNDI name of this resource.

# Examples

## Example 1 Creating a Managed Executor Service Resource

This example creates a managed executor service resource named `concurrent/myExecutor`.

```
asadmin> create-managed-executor-service concurrent/myExecutor
Managed executor service concurrent/myExecutor created successfully.
Command create-managed-executor-service executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-managed-executor-service\(1\)](#), [list-managed-executor-services\(1\)](#)

# create-managed-scheduled-executor-service

Creates a managed scheduled executor service resource

## Synopsis

```
asadmin [asadmin-options] create-managed-scheduled-executor-service [--help]
[--enabled={false|true}]
[--contextinfoenabled={false|true}]
[--contextinfo={Classloader|JNDI|Security|WorkArea}]
[--threadpriority threadpriority]
[--longrunningtasks={false|true}]
[--hungafterseconds hungafterseconds]
[--hungloggerprintonce={false|true}]
[--hungloggerinitialdelayseconds hungloggerinitialdelayseconds]
[--hungloggerintervalseconds hungloggerintervalseconds]
[--corepoolsize corepoolsize]
[--keepaliveseconds keepaliveseconds]
[--threadlifetimeseconds threadlifetimeseconds]
[--description description]
[--property property]
[--target target]
jndi_name
```

## Description

The `create-managed-scheduled-executor-service` subcommand creates a managed scheduled executor service resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--enabled**

Determines whether the resource is enabled at runtime. The default value is `true`.

**--contextinfoenabled**

Determines whether container contexts are propagated to threads. If set to `true`, the contexts specified in the `--contextinfo` option are propagated. If set to `false`, no contexts are propagated and the `--contextinfo` option is ignored. The default value is `true`.

**--contextinfo**

Specifies individual container contexts to propagate to threads. Valid values are Classloader, JNDI, Security, and WorkArea. Values are specified in a comma-separated list and are case-insensitive. All contexts are propagated by default.

**--threadpriority**

Specifies the priority to assign to created threads. The default value is 5.

**--longrunningtasks**

Specifies whether the resource should be used for long-running tasks. The default value is `false`. If set to `true`, long-running tasks are not reported as stuck.

**--hungafterseconds**

Specifies the number of seconds that a task can execute before it is considered unresponsive. The default value is 0, which means that tasks are never considered unresponsive.

**--hungloggerprintonce**

Specifies whether to print the warning message once or repeatedly. The default value is false. If set to true, the warning message is printed only once when detect a hung task exceeds "hungafterseconds".

**--hungloggerinitialdelayseconds**

Specifies the number of seconds to delay logging the detection of hung tasks. The default value is 60.

**--hungloggerintervalseconds**

Specifies the number of seconds between logging the detection of hung tasks. The default value is 60.

**--corepoolsize**

Specifies the number of threads to keep in a thread pool, even if they are idle. The default value is 0, which means that a thread is created when the first task is scheduled.

**--keepaliveseconds**

Specifies the number of seconds that threads can remain idle when the number of threads is greater than `corepoolsize`. The default value is 60.

**--threadlifetimeseconds**

Specifies the number of seconds that threads can remain in a thread pool before being purged, regardless of whether the number of threads is greater than `corepoolsize` or whether the threads are idle. The default value is 0, which means that threads are never purged.

**--description**

Descriptive details about the resource.

**--property**

Optional attribute name/value pairs for configuring the resource.

Eclipse GlassFish does not define any additional properties for this resource. Moreover, this resource does not currently use any additional properties.

**--target**

Specifies the target for which you are creating the resource. Valid targets are:

**server**

Creates the resource for the default server instance. This is the default value.

**domain**

Creates the resource for the domain.

**cluster\_name**

Creates the resource for every server instance in the specified cluster.

**instance\_name**

Creates the resource for the specified server instance.

## Operands

**jndi\_name**

The JNDI name of this resource.

## Examples

### Example 1 Creating a Managed Scheduled Executor Service Resource

This example creates a managed scheduled executor service resource named `concurrent/myScheduledExecutor`.

```
asadmin> create-managed-scheduled-executor-service concurrent/myScheduledExecutor
Managed scheduled executor service concurrent/myScheduledExecutor created successfully.
Command create-managed-scheduled-executor-service executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-managed-scheduled-executor-service\(1\)](#), [list-managed-scheduled-executor-services\(1\)](#)

# create-managed-thread-factory

Creates a managed thread factory resource

## Synopsis

```
asadmin [asadmin-options] create-managed-thread-factory [--help]
[--enabled={false|true}]
[--contextinfoenabled={false|true}]
[--contextinfo={Classloader|JNDI|Security|WorkArea}]
[--threadpriority threadpriority]
[--description description]
[--property property]
[--target target]
jndi_name
```

## Description

The `create-managed-thread-factory` subcommand creates a managed thread factory resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--enabled**

Determines whether the managed thread factory is enabled at runtime. The default value is `true`.

**--contextinfoenabled**

Determines whether container contexts are propagated to threads. If set to `true`, the contexts specified in the `--contextinfo` option are propagated. If set to `false`, no contexts are propagated and the `--contextinfo` option is ignored. The default value is `true`.

**--contextinfo**

Specifies individual container contexts to propagate to threads. Valid values are Classloader, JNDI, Security, and WorkArea. Values are specified in a comma-separated list and are case-insensitive. All

contexts are propagated by default.

#### --threadpriority

Specifies the priority to assign to created threads. The default value is 5.

#### --description

Descriptive details about the resource.

#### --property

Optional attribute name/value pairs for configuring the resource.

Eclipse GlassFish does not define any additional properties for this resource. Moreover, this resource does not currently use any additional properties.

#### --target

Specifies the target for which you are creating the resource. Valid targets are:

##### **server**

Creates the resource for the default server instance. This is the default value.

##### **domain**

Creates the resource for the domain.

##### **cluster\_name**

Creates the resource for every server instance in the specified cluster.

##### **instance\_name**

Creates the resource for the specified server instance.

## Operands

### jndi\_name

The JNDI name of this resource.

## Examples

### Example 1 Creating a Managed Thread Factory Resource

This example creates a managed thread factory resource named `concurrent/myThreadFactory`.

```
asadmin> create-managed-thread-factory concurrent/myThreadFactory  
Managed thread factory concurrent/myThreadFactory created successfully.  
Command create-managed-thread-factory executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-managed-thread-factory\(1\)](#), [list-managed-thread-factories\(1\)](#)

# create-message-security-provider

Enables administrators to create a message security provider, which specifies how SOAP messages will be secured.

## Synopsis

```
asadmin [asadmin-options] create-message-security-provider [--help]
[--target target]
--classname provider_class
[--layer message_layer] [--provider_type provider_type]
[--requestauthsource request_auth_source ]
[--requestauthrecipient request_auth_recipient ]
[--responseauthsource response_auth_source ]
[--responseauthrecipient response_auth_recipient ]
[--isdefaultprovider] [--property name=value[:name=value]*]
provider_name
```

## Description

The **create-message-security-provider** subcommand enables the administrator to create a message security provider for the security service which specifies how SOAP messages will be secured.

This command is supported in remote mode only.

## Options

If an option has a short option name, then the short option precedes the long option name. Short options have one dash whereas long options have two dashes.

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### **--target**

Specifies the target for which you are creating the message security provider. The following values are valid:

**server**

Creates the provider for the default server instance **server** and is the default value.

**domain**

Creates the provider for the domain.

**cluster\_name**

Creates the provider for every server instance in the cluster.

**instance\_name**

Creates the provider for a particular sever instance.

**--classname**

Defines the Java implementation class of the provider. Client authentication providers must implement the `com.sun.enterprise.security.jauth.ClientAuthModule` interface. Server-side providers must implement the `com.sun.enterprise.security.jauth.ServerAuthModule` interface. A provider may implement both interfaces, but it must implement the interface corresponding to its provider type.

**--layer**

The message-layer entity used to define the value of the `auth-layer` attribute of `message-security-config` elements. The default is `HttpServlet`. Another option is `SOAP`.

**--provider-type**

Establishes whether the provider is to be used as client authentication provider, server authentication provider, or both. Valid options for this property include `client`, `server`, or `client-server`.

**--request-auth-source**

The `auth-source` attribute defines a requirement for message-layer sender authentication (e.g. username password) or content authentication (e.g. digital signature) to be applied to request messages. Possible values are `sender` or `content`. When this argument is not specified, source authentication of the request is not required.

**--request-auth-recipient**

The `auth-recipient` attribute defines a requirement for message-layer authentication of the receiver of a message to its sender (e.g. by XML encryption). Possible values are `before-content` or `after-content`. The default value is `after-content`.

**--response-auth-source**

The `auth-source` attribute defines a requirement for message-layer sender authentication (e.g. username password) or content authentication (e.g. digital signature) to be applied to response messages. Possible values are `sender` or `content`. When this option is not specified, source authentication of the response is not required.

## --responseauthrecipient

The `auth-recipient` attribute defines a requirement for message-layer authentication of the receiver of the response message to its sender (e.g. by XML encryption). Possible values are `before-content` or `after-content`. The default value is `after-content`.

## --isdefaultprovider

The `default-provider` attribute is used to designate the provider as the default provider (at the layer) of the type or types identified by the `provider-type` argument. There is no default associated with this option.

## --property

Use this property to pass provider-specific property values to the provider when it is initialized. Properties passed in this way might include key aliases to be used by the provider to get keys from keystores, signing, canonicalization, encryption algorithms, etc.

The following properties may be set:

### `security.config`

Specifies the location of the message security configuration file. To point to a configuration file in the domain-dir/`config` directory, use the system property  `${com.sun.aas.instanceRoot}/config/`, for example:  `${com.sun.aas.instanceRoot}/config/wss-server-config-1.0.xml`. The default is domain-dir`/config/ wss-serverconfig-1.0.xml`.

### `debug`

If `true`, enables dumping of server provider debug messages to the server log. The default is `false`.

### `dynamic.username.password`

If `true`, signals the provider runtime to collect the user name and password from the `CallbackHandler` for each request. If `false`, the user name and password for `wsse:UsernameToken`(s) is collected once, during module initialization. This property is only applicable for a `ClientAuthModule`. The default is `false`.

### `encryption.key.alias`

Specifies the encryption key used by the provider. The key is identified by its keystore alias. The default value is `s1as`.

### `signature.key.alias`

Specifies the signature key used by the provider. The key is identified by its keystore alias. The default value is `s1as`.

# Operands

## `provider_name`

The name of the provider used to reference the `provider-config` element.

# Examples

## Example 1 Creating a Message Security Provider

The following example shows how to create a message security provider for a client.

```
asadmin> create-message-security-provider  
--classname com.sun.enterprise.security.jauth.ClientAuthModule  
--providername mySecurityProvider
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[delete-message-security-provider\(1\)](#), [list-message-security-providers\(1\)](#)

# create-module-config

Adds the default configuration of a module to `domain.xml`

## Synopsis

```
asadmin [asadmin-options] create-module-config [--help]
[--dryrun={false|true}]
[--all={false|true}]
[--target target]
[service_name]
```

## Description

The `create-module-config` subcommand adds the default configuration of a module to `domain.xml`.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

`-?`

Displays the help text for the subcommand.

#### --dryrun

Displays the default configuration of a module but does not add it to `domain.xml`. The default value is `false`.

#### --all

Adds all default configurations of modules to `domain.xml` if they are not already in it. The default value is `false`.

#### --target

Specifies the target to which the default configuration is being added. Possible values are as follows:

##### server

Adds the default configuration to the default server instance. This is the default value.

**domain**

Adds the default configuration to the default domain.

**cluster-name**

Adds the default configuration to every server instance in the specified cluster.

**instance-name**

Adds the default configuration to the specified instance.

## Operands

**service\_name**

The name of the module for which the default configuration is to be added.

## Examples

### Example 1 Adding a Default Configuration to domain.xml

This example adds the default configuration of the web container module to `domain1` in `server-config` (the default configuration). Use the `--dryrun` option to preview the configuration before it is added.

```
asadmin> create-module-config web-container
Command create-module-config executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-module-config\(1\)](#), [get-active-module-config\(1\)](#)

# create-network-listener

Adds a new network listener socket

## Synopsis

```
asadmin [asadmin-options] create-network-listener [--help]
[--address address]
--listenerport listener-port
[--threadpool thread-pool]
--protocol protocol
[--transport transport]
[--enabled={true|false}]
[--jkenabled={false|true}]
[--target target]
listener-name
```

## Description

The `create-network-listener` subcommand creates a network listener. This subcommand is supported in remote mode only.



If you edit the special network listener named `admin-listener`, you must restart the server for the changes to take effect. The Administration Console does not tell you that a restart is required in this case.



You can use the `create-http-listener` subcommand to create a network listener that uses the HTTP protocol without having to first create a protocol, transport, or HTTP configuration. This subcommand is a convenient shortcut, but it gives access to only a limited number of options.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--address**

The IP address or the hostname (resolvable by DNS).

**--listenerport**

The port number to create the listen socket on. Legal values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges. Configuring an SSL listen socket to listen on port 443 is standard.

**--threadpool**

The name of the thread pool for this listener. Specifying a thread pool is optional. The default is `http-thread-pool`.

**--protocol**

The name of the protocol for this listener.

**--transport**

The name of the transport for this listener. Specifying a transport is optional. The default is `tcp`.

**--enabled**

If set to `true`, the default, the listener is enabled at runtime.

**--jkenabled**

If set to `true`, `mod_jk` is enabled for this listener. The default is false.

**--target**

Creates the network listener only on the specified target. Valid values are as follows:

**server**

Creates the network listener on the default server instance. This is the default value.

**configuration-name**

Creates the network listener in the specified configuration.

**cluster-name**

Creates the network listener on all server instances in the specified cluster.

**standalone-instance-name**

Creates the network listener on the specified standalone server instance.

# Operands

**listener-name**

The name of the network listener.

# Examples

## Example 1 Creating a Network Listener

The following command creates a network listener named `sampleListener` that is not enabled at runtime:

```
asadmin> create-network-listener --listenerport 7272 protocol http-1  
--enabled=false sampleListener  
Command create-network-listener executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-http-listener\(1\)](#), [create-protocol\(1\)](#), [create-threadpool\(1\)](#), [create-transport\(1\)](#), [delete-network-listener\(1\)](#), [list-network-listeners\(1\)](#)

# create-node-config

Creates a node that is not enabled for remote communication

## Synopsis

```
asadmin [asadmin-options] create-node-config [--help]
[--nodehost node-host]
[--installdir as-install-parent] [--nodedir node-dir] node-name
```

## Description

The `create-node-config` subcommand creates a node that is not enabled for remote communication. The `create-node-config` subcommand does not require the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured to create the node.

A node represents a host on which the Eclipse GlassFish software is installed. A node must exist for every host on which Eclipse GlassFish instances reside.



To represent the host where the DAS is running, Eclipse GlassFish provides the predefined node `localhost`-domain. The predefined node `localhost`-domain is not enabled for remote communication.

All administration of instances on a node that is not enabled for remote communication must be performed on the host that the node represents. The domain administration server (DAS) on a remote host cannot contact the node. To administer instances on a node that represents a host that is remote from the DAS, you must use the following subcommands:

- `create-local-instance(1)`
- `delete-local-instance(1)`
- `start-local-instance(1)`

However, you may use `stop-local-instance(1)` or `stop-instance(1)` to stop the instances.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

**--help****-?**

Displays the help text for the subcommand.

**--nodehost**

The name of the host that the node represents. If this option is omitted, no host is specified for the node.

**--installdir**

The full path to the parent of the base installation directory of the Eclipse GlassFish software on the host, for example, `/export/glassfish7/`. If this option is omitted, no parent of the base installation directory of the Eclipse GlassFish software is specified for the node.

**--nodedir**

The path to the directory that is to contain Eclipse GlassFish instances that are created on the node. If a relative path is specified, the path is relative to the as-install directory. If this option is omitted, no directory for instances is specified for the node.

# Operands

**node-name**

The name of the node.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period
  - Underscore
- The name must be unique in the domain and must not be the name of another node, a cluster, a named configuration, or a Eclipse GlassFish instance.
- The name must not be `domain`, `server`, or any other keyword that is reserved by Eclipse GlassFish.

# Examples

## Example 1 Creating a Node That Is Not Enabled for Remote Communication

This example creates the node `sj03` for host `sj03.example.com`. The node is not enabled for remote communication.

```
asadmin> create-node-config --nodehost sj03.example.com sj03
```

```
Command create-node-config executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-local-instance\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-local-instance\(1\)](#), [delete-node-config\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-nodes\(1\)](#), [start-local-instance\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-config\(1\)](#), [update-node-dcom\(1\)](#), [update-node-ssh\(1\)](#)

# create-node-dcom

Creates a node that is enabled for communication over DCOM

## Synopsis

```
asadmin [asadmin-options] create-node-dcom [--help]
--nodehost node-host
[--installdir as-install-parent] [--nodedir node-dir]
[--windowsuser windows-user] [--windowsdomain windows-domain]
[--force={false|true}]
[--install={false|true}] [--archive archive]
node-name
```

## Description

The `create-node-dcom` subcommand creates a node that is enabled for communication over the Distributed Component Object Model (DCOM) remote protocol. The DCOM protocol is available only on Windows systems.

A node represents a host on which the Eclipse GlassFish software is installed. A node must exist for every host on which Eclipse GlassFish instances reside.

In a DCOM-enabled network, the domain administration server (DAS) contacts a node's host through the DCOM connector to manage Eclipse GlassFish instances that reside on the node. DCOM is used only for communications between hosts. DCOM is never used for communications within a single host.

By default, the subcommand fails and the node is not created if the DAS cannot contact the node's host through DCOM. To force the node to be created in the DAS configuration even if the host cannot be contacted through DCOM, set the `--force` option to `true`.

The `create-node-dcom` subcommand cannot create a node that represents the local host, that is, the host on which the subcommand is run. The subcommand fails regardless of how the local host is specified, for example, by using the keyword `localhost`, the Internet Protocol (IP) address of the host, or the host name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--nodehost**

The name of the host that the node represents. The name of the host must be specified. Otherwise, an error occurs.

**--installdir**

The full path to the parent of the base installation directory of the Eclipse GlassFish software on the host, for example, `C:\glassfish7`. The default is the parent of the default base installation directory of the Eclipse GlassFish software for the DAS. This default is useful only if Eclipse GlassFish is installed in the same location on all hosts.

**--nodedir**

The path to the directory that is to contain Eclipse GlassFish instances that are created on the node. The default is `as-install`\nodes``, where `as-install` is the base installation directory of the Eclipse GlassFish software on the host. If a relative path is specified, the path is relative to the `as-install` directory.

**--windowsuser****-W**

The user on this node's host that is to run the process for connecting to the host through DCOM. The default is the user that is running the DAS process. If the `--nodehost` option is set to `localhost-domain`, the `--windowsuser` option is ignored

**--windowsdomain****-d**

The name of the Windows domain that contains the user that the `--windowsuser` option specifies. The default is the name of the host on which the subcommand is run.

**--force**

Specifies whether the node is created in the DAS configuration even if validation of the node's parameters fails. To validate a node's parameters, the DAS must be able to contact the node's host through DCOM. Possible values are as follows:

**false**

The node is not created if validation of the node's parameters fails (default).

**true**

The node is created even if validation of the node's parameters fails.

**--install**

Specifies whether the subcommand shall install the Eclipse GlassFish software on the host that the

node represents.

Possible values are as follows:

#### false

The subcommand shall not install the Eclipse GlassFish software on the host (default).

#### true

The subcommand shall install the Eclipse GlassFish software on the host.

#### --archive

The absolute path to the archive file of the Eclipse GlassFish software that is to be installed. If this option is omitted and the --install is true, the subcommand creates a ZIP archive of the Eclipse GlassFish software from the installation where this subcommand is run. The archive does not contain the domains directory or the nodes directory.

## Operands

### node-name

The name of the node.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period
  - Underscore
- The name must be unique in the domain and must not be the name of another node, a cluster, a named configuration, or a Eclipse GlassFish instance.
- The name must not be domain, server, or any other keyword that is reserved by Eclipse GlassFish.

## Examples

## Example 1 Creating a Node

This example creates the node `wpmdl1` for the host `wpmdl1.example.com`. By default, the parent of the base installation directory of the Eclipse GlassFish software is `C:\glassfish7`.

```
asadmin> create-node-dcom  
--nodehost wpmdl1.example.com wpmdl1  
Command create-node-dcom executed successfully.
```

## Example 2 Creating a Node With a Specific Installation Directory

This example creates the node `wym11` for the host `wym11.example.com`. The parent of the base installation directory of the Eclipse GlassFish software on this host is `C:\middleware\glassfish7`.

```
asadmin> create-node-dcom --installdir C:\middleware\glassfish7  
--nodehost wym11.example.com wym11  
Command create-node-dcom executed successfully.
```

## Example 3 Forcing the Creation of a Node

This example forces the creation of node `xkyd` for the host `xkyd.example.com`. The node is created despite the failure of the DAS to contact the host `xkyd.example.com` to validate the node's parameters.

```
asadmin> create-node-dcom --force --nodehost xkyd.example.com xkyd  
Warning: some parameters appear to be invalid.  
com.sun.enterprise.universal.process.WindowsException: Connection in error  
Continuing with node creation due to use of --force.  
Command create-node-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-dcom\(1\)](#), [install-node-dcom\(1\)](#), [list-nodes\(1\)](#),  
[uninstall-node-dcom\(1\)](#), [update-node-dcom\(1\)](#)

# create-node-ssh

Creates a node that is enabled for communication over SSH

## Synopsis

```
asadmin [asadmin-options] create-node-ssh [--help]
--nodehost node-host
[--installdir as-install-parent] [--nodedir node-dir]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile]
[--force={false|true}]
[--install={false|true}] [--archive archive]
node-name
```

## Description

The `create-node-ssh` subcommand creates a node that is enabled for communication over secure shell (SSH).

A node represents a host on which the Eclipse GlassFish software is installed. A node must exist for every host on which Eclipse GlassFish instances reside.

The domain administration server (DAS) contacts an SSH node's host through the SSH connector to manage Eclipse GlassFish instances that reside on the node. However, the DAS does not use the SSH connector to contact the host where the DAS is running because the DAS can run all `asadmin` subcommands locally.

By default, the subcommand fails and the node is not created if the DAS cannot contact the node's host through SSH. To force the node to be created in the DAS configuration even if the host cannot be contacted through SSH, set the `--force` option to `true`.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--nodehost**

The name of the host that the node represents. The name of the host must be specified. Otherwise, an error occurs.

**--installdir**

The full path to the parent of the base installation directory of the Eclipse GlassFish software on the host, for example, `/export/glassfish7/`. The default is the parent of the default base installation directory of the Eclipse GlassFish software for the DAS. This default is useful only if Eclipse GlassFish is installed in the same location on all hosts.

**--nodedir**

The path to the directory that is to contain Eclipse GlassFish instances that are created on the node. The default is `as-install/nodes`, where `as-install` is the base installation directory of the Eclipse GlassFish software on the host. If a relative path is specified, the path is relative to the `as-install` directory.

**--sshport**

The port to use for SSH connections to this node's host. The default is 22. If the `--nodehost` option is set to `localhost`-domain, the `--sshport` option is ignored.

**--sshuser**

The user on this node's host that is to run the process for connecting to the host through SSH. The default is the user that is running the DAS process. To ensure that the DAS can read this user's SSH private key file, specify the user that is running the DAS process. If the `--nodehost` option is set to `localhost`-domain, the `--sshuser` option is ignored.

**--sshkeyfile**

The absolute path to the SSH private key file for user that the `--sshuser` option specifies. This file is used for authentication to the `sshd` daemon on the node's host.



Eclipse GlassFish also supports password authentication through the `AS_ADMIN_SSHPASSWORD` entry in the password file. The password file is specified in the `--passwordfile` option of the `asadmin(1M)` utility.

If the SSH private key file is protected by a passphrase, the password file must contain the `AS_ADMIN_SSHKEYPASSPHRASE` entry.

The path to the key file must be reachable by the DAS and the key file must be readable by the DAS. The default is the a key file in the user's `.ssh` directory. If multiple key files are found, the subcommand uses the following order of preference:

1. `id_rsa`
2. `id_dsa`
3. `identity`

**--force**

Specifies whether the node is created in the DAS configuration even if validation of the node's parameters fails. To validate a node's parameters, the DAS must be able to contact the node's host through SSH. Possible values are as follows:

**false**

The node is not created if validation of the node's parameters fails (default).

**true**

The node is created even if validation of the node's parameters fails.

**--install**

Specifies whether the subcommand shall install the Eclipse GlassFish software on the host that the node represents.

Possible values are as follows:

**false**

The subcommand shall not install the Eclipse GlassFish software on the host (default).

**true**

The subcommand shall install the Eclipse GlassFish software on the host.

**--archive**

The absolute path to the archive file of the Eclipse GlassFish software that is to be installed. If this option is omitted and the **--install** is **true**, the subcommand creates a ZIP archive of the Eclipse GlassFish software from the installation where this subcommand is run. The archive does not contain the **domains** directory or the **nodes** directory.

# Operands

**node-name**

The name of the node.

The name must meet the following requirements:

- The name may contain only ASCII characters.
- The name must start with a letter, a number, or an underscore.
- The name may contain only the following characters:
  - Lowercase letters
  - Uppercase letters
  - Numbers
  - Hyphen
  - Period

- Underscore
- The name must be unique in the domain and must not be the name of another node, a cluster, a named configuration, or a Eclipse GlassFish instance.
- The name must not be `domain`, `server`, or any other keyword that is reserved by Eclipse GlassFish.

## Examples

### Example 1 Creating a Node

This example creates the node `adc` for the host `adc.example.com`. By default, the parent of the base installation directory of the Eclipse GlassFish software is `/export/glassfish7`.

```
asadmin> create-node-ssh
--nodehost adc.example.com
--installdir /export/glassfish7 adc
```

Command `create-node-ssh` executed successfully.

### Example 2 Forcing the Creation of a Node

This example forces the creation of node `eg1` for the host `eghost.example.com`. The node is created despite the failure of the DAS to contact the host `eghost.example.com` to validate the node's parameters.

```
asadmin> create-node-ssh --force --nodehost eghost.example.com eg1
Warning: some parameters appear to be invalid.
Could not connect to host eghost.example.com using SSH.
There was a problem while connecting to eghost.example.com:22
eghost.example.com
Continuing with node creation due to use of --force.
```

Command `create-node-ssh` executed successfully.

## Exit Status

**0**

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-ssh\(1\)](#),  
[list-nodes\(1\)](#), [ping-node-ssh\(1\)](#), [setup-ssh\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-ssh\(1\)](#)

# create-password-alias

Creates a password alias

## Synopsis

```
asadmin [asadmin-options] create-password-alias [--help]
aliasname
```

## Description

The `create-password-alias` subcommand creates an alias for a password. An alias is a token of the form `ALIAS=aliasname`. The password that corresponds to the alias name is stored in an encrypted form.

The `create-password-alias` subcommand can be run interactively or noninteractively.

- When run interactively, the subcommand prompts the user for the alias password and to confirm the alias password.
- When run noninteractively, the subcommand reads the alias password from a file that is passed through the `--passwordfile` option of the [asadmin\(1M\)](#) utility. The file must contain an entry of the form ` {cprefix}ALIASPASSWORD=alias-password, where alias-password is the alias password. The noninteractive form of this command is suitable for use in scripts.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### aliasname

Your choice of name for the password alias.

# Examples

## Example 1 Creating a Password Alias Interactively

This example creates the password alias `jmspassword-alias` interactively.

```
asadmin> create-password-alias jmspassword-alias  
Enter the alias password>  
Enter the alias password again>  
Command create-password-alias executed successfully.
```

## Example 2 Creating a Password Alias Noninteractively

This example uses the `--passwordfile` option of the `asadmin` utility to create the password alias `winuser` noninteractively.

```
$ asadmin --passwordfile aspwfile.txt create-password-alias winuser  
Command create-password-alias executed successfully.
```

The file `aspwfile.txt` contains the following entry to specify the alias password:

```
AS_ADMIN_ALIASPASSWORD=sp@rky
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[delete-password-alias\(1\)](#), [list-password-aliases\(1\)](#), [update-password-alias\(1\)](#)

# create-profiler

Creates the profiler element

## Synopsis

```
asadmin [asadmin-options] create-profiler [--help]
[--target target_name]
[--classpath classpath] [--nativelibpath native_library_path] [--enabled=true]
[--property(name=value)[:name=value]*] profiler_name
```

## Description

The **create-profiler** subcommand creates the profiler element. A server instance is tied to the profiler by the profiler element in the Java configuration. Only one profiler exists at a time. If you attempt to create a profiler while one already exists, an error message is displayed.

For changes to take effect, the server must restarted.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This option specifies the target on which you are creating a profiler. Valid values are

**server**

Creates the profiler for the default server instance. This is the default value.

**configuration\_name**

Creates the profiler for the named configuration

**cluster\_name**

Creates the profiler for every server instance in the cluster

**instance\_name**

Creates the profiler for a particular server instance

**--classpath**

Java classpath string that specifies the classes needed by the profiler.

**--nativelibpath**

This path is automatically constructed to be a concatenation of the Eclipse GlassFish installation relative path for its native shared libraries, standard JRE native library path, the shell environment setting (`LD_LIBRARY_PATH` on UNIX) and any path that may be specified in the profile element.

**--enabled**

Profiler is enabled by default.

**--property**

Name/value pairs of provider-specific attributes.

## Operands

**profiler\_name**

Name of the profiler.

## Examples

### Example 1 Creating a Profiler

This example creates a profiler named `sample_profiler`.

```
asadmin> create-profiler --classpath /home/appserver/
--nativelibpath /u/home/lib --enabled=false
--property defaultuser=admin:password=adminadmin sample_profiler
Created Profiler with id = sample_profiler
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[delete-profiler\(1\)](#)

# create-protocol

Adds a new protocol

## Synopsis

```
asadmin [asadmin-options] create-protocol [--help]
[--securityenabled={false|true}]
[--target target]
protocol-name
```

## Description

The **create-protocol** subcommand creates a protocol. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --securityenabled

If set to **true**, the protocol runs SSL. You can turn SSL2 or SSL3 ON or OFF and set ciphers using an **ssl** element. The security setting globally enables or disables SSL by making certificates available to the server instance. The default value is **false**.

#### --target

Creates the protocol only on the specified target. Valid values are as follows:

##### server

Creates the protocol on the default server instance. This is the default value.

##### configuration-name

Creates the protocol in the specified configuration.

##### cluster-name

Creates the protocol on all server instances in the specified cluster.

**standalone-instance-name**

Creates the protocol on the specified standalone server instance.

# Operands

**protocol-name**

The name of the protocol.

# Examples

## Example 1 Creating a Protocol

The following command creates a protocol named `http-1` with security enabled:

```
asadmin> create-protocol --securityenabled=true http-1
Command create-protocol executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[delete-protocol\(1\)](#), [list-protocols\(1\)](#), [create-network-listener\(1\)](#)

# create-protocol-filter

Adds a new protocol filter

## Synopsis

```
asadmin [asadmin-options] create-protocol-filter [--help]
--protocol protocol-name
--classname class-name
[--target server]
protocol-filter-name
```

## Description

The `create-protocol-filter` subcommand creates a protocol filter for a protocol. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --protocol

The name of the associated protocol.

#### --classname

The fully qualified name of the Java class that implements the protocol filter.

#### --target

Creates the protocol filter only on the specified target. Valid values are as follows:

##### server

Creates the protocol filter on the default server instance. This is the default value.

#### configuration-name

Creates the protocol filter in the specified configuration.

**cluster-name**

Creates the protocol filter on all server instances in the specified cluster.

**standalone-instance-name**

Creates the protocol filter on the specified standalone server instance.

# Operands

**protocol-filter-name**

The name of the protocol filter.

# Examples

## Example 1 Creating a Protocol Filter

The following command creates a protocol filter named `http1-filter`:

```
asadmin> create-protocol-filter --protocol http1  
--classname com.company22.MyProtocolFilter http1-filter  
Command create-protocol-filter executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-protocol\(1\)](#), [delete-protocol-filter\(1\)](#), [list-protocol-filters\(1\)](#)

# create-protocol-finder

Adds a new protocol finder

## Synopsis

```
asadmin [asadmin-options] create-protocol-finder [--help]
--protocol protocol-name
--targetprotocol target-protocol-name
--classname class-name
[--target server]
protocol-finder-name
```

## Description

The **create-protocol-finder** subcommand creates a protocol finder for a protocol. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --protocol

The name of the associated protocol.

#### --targetprotocol

The name of the target protocol.

#### --classname

The fully qualified name of the Java class that implements the protocol finder.

#### --target

Creates the protocol finder only on the specified target. Valid values are as follows:

#### server

Creates the protocol finder on the default server instance. This is the default value.

**configuration-name**

Creates the protocol finder in the specified configuration.

**cluster-name**

Creates the protocol finder on all server instances in the specified cluster.

**standalone-instance-name**

Creates the protocol finder on the specified standalone server instance.

# Operands

**protocol-finder-name**

The name of the protocol finder.

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[delete-protocol-finder\(1\)](#), [list-protocol-finders\(1\)](#)

# create-resource-adapter-config

Creates the configuration information for the connector module

## Synopsis

```
asadmin [asadmin-options] create-resource-adapter-config [--help]
[--threadpoolid threadpool]
[--objecttype object-type]
[--property (property-name=value)[:name=value]*]
[rename]
```

## Description

The **create-resource-adapter-config** subcommand creates configuration information for the connector module. This subcommand can be run before deploying a resource adapter, so that the configuration information is available at the time of deployment. The resource adapter configuration can also be created after the resource adapter is deployed. In this case, the resource adapter is restarted with the new configuration. You must first create a thread pool, using the **create-threadpool** subcommand, and then identify that thread pool value as the ID in the **--threadpoolid** option.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

This option has been deprecated.

#### --threadpoolid

The thread pool ID from which the work manager gets the thread. This option takes only one thread pool ID.

#### --objecttype

The default is **user**.

## --property

Keyword-value pairs that specify additional configuration properties of the resource adapter Java bean. The keyword-value pairs are separated by a colon (:). The properties are the names of setter methods of the class that is referenced by the `resourceadapter-class` element in the `ra.xml` file.

# Operands

## raname

Indicates the connector module name. It is the value of the `resource-adapter-name` in the `domain.xml` file.

# Examples

## Example 1 Creating a Resource Adapter Configuration

This example creates a resource adapter configuration for `ra1`.

```
asadmin> create-resource-adapter-config --property foo=bar --threadpoolid  
mycustomerthreadpool ra1  
Command create-resource-adapter-config executed successfully
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-threadpool\(1\)](#), [delete-resource-adapter-config\(1\)](#), [list-resource-adapter-configs\(1\)](#)

# create-resource-ref

Creates a reference to a resource

## Synopsis

```
asadmin [asadmin-options] create-resource-ref [--help]
[--target target]
[--enabled={false|true}] reference_name
```

## Description

The `create-resource-ref` subcommand creates a reference from a cluster or an unclustered server instance to a previously created resource, for example, a JDBC resource created by using the `create-jdbc-resource` subcommand. This effectively results in the resource being made available in the JNDI tree of the instance or cluster.

The target instance or instances making up the cluster need not be running or available for this subcommand to succeed. If one or more instances are not available, they will receive the new resource the next time they start.

A `resource-ref` can only be created for bindable resources, such as a `jdbc-resource`, `connector-resource`, `admin-object-resource`, `mail-resource`, `custom-resource`, or `jndi-resource`.



A `jdbc-connection-pool` or a `connector-connection-pool` are not referred to directly by applications. Instead, they are referred to through a `jdbc-resource` or `connector-resource`, respectively.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target for which you are creating the resource reference. Valid targets are as follows:

**server**

Creates the resource reference for the default server instance. This is the default target.

**cluster\_name**

Creates the resource reference for every server instance in the cluster.

**instance\_name**

Creates the resource reference for the named unclustered server instance.

**--enabled**

Indicates whether the resource should be enabled. This value will take effect only if the resource is enabled at the global level. The default is **true**.

# Operands

**reference\_name**

The name or JNDI name of the resource.

# Examples

## Example 1 Creating a Reference to a JMS Destination Resource

This example creates a reference to the JMS destination resource **jms/Topic** on the cluster **Cluster1**.

```
asadmin> create-resource-ref --target Cluster1 jms/Topic  
resource-ref jms/Topic created successfully.  
Command create-resource-ref executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[delete-resource-ref\(1\)](#), [list-resource-refs\(1\)](#)

# create-service

Configures the starting of a DAS or a Eclipse GlassFish instance on an unattended boot

## Synopsis

```
asadmin [asadmin-options] create-service [--help]
[--name service-name]
[--serviceproperties service-properties]
[--dry-run={false|true}] [--force={false|true}]
[--serviceuser service-user]
[--domaindir domain-dir]
[--nodedir node-dir] [--node node]
[domain-or-instance-name]
```

## Description

The **create-service** subcommand configures the starting of a domain administration server (DAS) or a Eclipse GlassFish instance on an unattended boot on Windows, Linux, and Oracle Solaris systems.

If no operand is specified and the domains directory contains only one domain, the subcommand configures the starting of the DAS for the default domain. If no operand is specified and the domains directory contains multiple domains, an error occurs.

If the operand specifies an instance, the **create-service** subcommand does not contact the domain administration server (DAS) to determine the node on which the instance resides. To determine the node on which the instance resides, the subcommand searches the directory that contains the node directories. If multiple node directories exist, the node must be specified as an option of the subcommand.

The subcommand contains internal logic to determine whether the supplied operand is a DAS or an instance.

This subcommand is supported in local mode only.

### Behavior of **create-service** on Windows Systems

On Windows systems, the **create-service** subcommand creates a Windows service to represent the DAS or instance. The service is created in the disabled state. After this subcommand creates the service, you must use the Windows Services Manager or the Windows Services Wrapper to start, stop, uninstall, or install the service.

On Windows systems, this subcommand must be run as the OS-level administrator user.

The subcommand creates the following Windows Services Wrapper files for the service in the domain-dir`\bin` directory or the instance-dir\bin directory:

- Configuration file: service-name**Service.xml**
- Executable file: service-name**Service.exe**

On Windows systems, this subcommand requires the Microsoft .NET Framework (<http://www.microsoft.com/net/>). Otherwise, the subcommand fails.

#### Behavior of **create-service** on Linux Systems

On Linux systems, the **create-service** subcommand creates a System-V-style initialization script `/etc/init.d/GlassFish_`domain-or-instance-name`` and installs a link to this script in the `'/etc/rc?.d'` directories. After this subcommand creates the script, you must use this script to start, stop, or restart the domain or instance.

On Linux systems, this subcommand must be run as the OS-level root user.

#### Behavior of **create-service** on Oracle Solaris Systems

On Oracle Solaris systems, the **create-service** subcommand creates a Service Management Facility (SMF) service to represent the DAS or instance. The service is created in the disabled state. After this subcommand creates the service, you must use SMF commands to start, enable, disable, delete, or stop the service. For more information about SMF, see the following documentation for the Oracle Solaris operating system:

- "[Managing Services \(Overview\)](#)" in System Administration Guide: Basic Administration
- "[Managing Services \(Tasks\)](#)" in System Administration Guide: Basic Administration

On Oracle Solaris systems, this subcommand must be run as the OS-level user with superuser privileges. The configuration file for the DAS or instance must be stored in a directory to which the superuser has access and cannot be stored on a network file system. The service that is created is controlled by the OS-level user who owns the directory where the configuration of the DAS or instance resides.

On Oracle Solaris systems, the manifest file is created in the following directory by default:

```
/var/svc/manifest/application/GlassFish/domain-or-instance-name_domain-or-instance-root-dir
```

To run this subcommand, you must have `solaris.smf.*` authorization. For information about how to grant authorizations to users, see the [useradd\(1M\)](#) and [usermod\(1M\)](#) man pages.

To run these commands as non-root user, the system administrator must be contacted so that the relevant authorizations are granted. You must also ensure that the following conditions are met:

- Oracle Solaris 10 administration commands such as `svccfg(1M)`, `svcs(1)`, and `aucts(1)` are available through the `PATH` statement, so that these commands can be executed. A simple test to do so is to run the command `which svccfg` in the shell.
- You must have write permission for the path `/var svc/manifest/application/GlassFish`. Usually, the superuser has write permission to this path.

If you delete a service that you created by using the `create-service` subcommand, you must delete the directory that contains the manifest file and the entire contents of the directory. Otherwise, an attempt to re-create the service by using the `create-service` subcommand fails. The Oracle Solaris command `svccfg` does not delete this directory.

## Options

### **asadmin-options**

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

#### **--help**

**-?**

Displays the help text for the subcommand.

#### **--name**

(Windows and Oracle Solaris systems only) The name of the service that you will use when administering the service through Oracle Solaris SMF commands or the service management features of the Windows operating system. The default is the name of the domain or instance that is specified as the operand of this subcommand.

#### **--serviceproperties**

Specifies a colon(:)-separated list of various properties that are specific to the service.

To customize the display name of the service in the Windows Service list, set the `DISPLAY_NAME` property to the required name.

For Oracle Solaris 10 systems, if you specify `net_privaddr`, the service's processes will be able to bind to the privileged ports (<1024) on the platform. You can bind to ports < 1024 only if the owner of the service is superuser, otherwise, this is not allowed.

#### **--dry-run**

**-n**

Previews your attempt to create a service. Indicates issues and the outcome that will occur if you run the command without using the `--dry-run` option. Nothing is actually configured. Default is false.

#### **--force**

Specifies whether the service is created even if validation of the service fails.

Possible values are as follows:

**true**

The service is created even if validation of the service fails.

**false**

The service is not created (default).

**--serviceuser**

(Linux systems only) The user that is to run the Eclipse GlassFish software when the service is started. The default is the user that is running the subcommand. Specify this option if the Eclipse GlassFish software is to be run by a user other than the root user.

**--domaindir**

The absolute path of the directory on the disk that contains the configuration of the domain. If this option is specified, the operand must specify a domain.

**--nodedir**

Specifies the directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is `as-install/nodes`. If this option is specified, the operand must specify an instance.

**--node**

Specifies the node on which the instance resides. This option may be omitted only if the directory that the `--nodedir` option specifies contains only one node directory. Otherwise, this option is required. If this option is specified, the operand must specify an instance.

## Operands

**domain-or-instance-name**

The name of the domain or instance to configure. If no operand is specified, the default domain is used.

## Examples

### Example 1 Creating a Service on a Windows System

This example creates a service for the default domain on a system that is running Windows.

```
asadmin> create-service
Found the Windows Service and successfully uninstalled it.
The Windows Service was created successfully. It is ready to be started. Here are
the details:
ID of the service: domain1
Display Name of the service:domain1 Eclipse GlassFish
Domain Directory: C:\glassfish7\glassfish\domains\domain1
Configuration file for Windows Services Wrapper: C:\glassfish7\glassfish\domains\
domain1\bin\domain1Service.xml
The service can be controlled using the Windows Services Manager or you can use the
Windows Services Wrapper instead:
Start Command: C:\glassfish7\glassfish\domains\domain1\bin\domain1Service.exe start
Stop Command: C:\glassfish7\glassfish\domains\domain1\bin\domain1Service.exe stop
Uninstall Command: C:\glassfish7\glassfish\domains\domain1\bin\domain1Service.exe
uninstall
Install Command: C:\glassfish7\glassfish\domains\domain1\bin\domain1Service.exe
install
```

This message is also available in a file named PlatformServices.log in the domain's root directory  
Command create-service executed successfully.

## Example 2 Creating a Service on a Linux System

This example creates a service for the default domain on a system that is running Linux.

```
asadmin> create-service
Found the Linux Service and successfully uninstalled it.
The Service was created successfully. Here are the details:
Name of the service:domain1
Type of the service:Domain
Configuration location of the service:/etc/init.d/GlassFish_domain1
User account that will run the service: root
You have created the service but you need to start it yourself.
Here are the most typical Linux commands of interest:

* /etc/init.d/GlassFish_domain1 start
* /etc/init.d/GlassFish_domain1 stop
* /etc/init.d/GlassFish_domain1 restart
```

For your convenience this message has also been saved to this file:  
/export/glassfish7/glassfish/domains/domain1/PlatformServices.log  
Command create-service executed successfully.

## Example 3 Creating a Service on an Oracle Solaris System

This example creates a service for the default domain on a system that is running Oracle Solaris.

```
asadmin> create-service
The Service was created successfully. Here are the details:
Name of the service:application/GlassFish/domain1
Type of the service:Domain
Configuration location of the service:/home/gfuser/glassfish-installations
/glassfish7/glassfish/domains
Manifest file location on the system:/var/svc/manifest/application
/GlassFish/domain1_home_gfuser_glassfish-installations_glassfish7
_glassfish_domains/Domain-service-smf.xml.
You have created the service but you need to start it yourself.
Here are the most typical Solaris commands of interest:
* /usr/bin/svcs -a | grep domain1 // status
* /usr/sbin/svcadm enable domain1 // start
* /usr/sbin/svcadm disable domain1 // stop
* /usr/sbin/svccfg delete domain1 // uninstall
Command create-service executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[auths\(1\)](#), [svcs\(1\)](#)

[svccfg\(1M\)](#), [useradd\(1M\)](#), [usermod\(1M\)](#)

"[Managing Services \(Overview\)](#)" in System Administration Guide: Basic Administration, "[Managing Services \(Tasks\)](#)" in System Administration Guide: Basic Administration

Microsoft .NET Framework (<http://www.microsoft.com/net/>)

# create-ssl

Creates and configures the SSL element in the selected HTTP listener, IIOP listener, or IIOP service

## Synopsis

```
asadmin [asadmin-options] create-ssl [--help]
[--target target]
--type listener_or_service_type
--certname cert_name
[--ssl2enabled={false|true}] [--ssl2ciphers ss12ciphers]
[--ssl3enabled={true|false}] [--t1senabled={true|false}]
[--ssl3tlsciphers ssl3tlsciphers]
[--tlsrollbackenabled={true|false}]
[--clientauthenabled={false|true}]
[listener_id]
```

## Description

The **create-ssl** subcommand creates and configures the SSL element in the selected HTTP listener, IIOP listener, or IIOP service to enable secure communication on that listener/service.

This subcommand is supported in remote mode only.

## Options

If an option has a short option name, then the short option precedes the long option name. Short options have one dash whereas long options have two dashes.

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target on which you are configuring the ssl element. The following values are valid:

**server**

Specifies the server in which the iiop-service or HTTP/IIOP listener is to be configured for SSL.

**config**

Specifies the configuration that contains the HTTP/IIO listener or iiop-service for which SSL is to be configured.

**cluster**

Specifies the cluster in which the HTTP/IIO listener or iiop-service is to be configured for SSL. All the server instances in the cluster will get the SSL configuration for the respective listener or iiop-service.

**instance**

Specifies the instance in which the HTTP/IIO listener or iiop-service is to be configured for SSL.

**--type**

The type of service or listener for which the SSL is created. The type can be:

- `network-listener`
- `http-listener`
- `iiop-listener`
- `iiop-service`
- `jmx-connector`

When the type is `iiop-service`, the `ssl-client-config` along with the embedded `ssl` element is created in `domain.xml`.

**--certname**

The nickname of the server certificate in the certificate database or the PKCS#11 token. The format of the name in the certificate is `tokenname:nickname`. For this property, the `tokenname:` is optional.

**--ssl2enabled**

Set this property to `true` to enable SSL2. The default value is `false`. If both SSL2 and SSL3 are enabled for a virtual server, the server tries SSL3 encryption first. In the event SSL3 encryption fails, the server then tries SSL2 encryption.

**--ssl2ciphers**

A comma-separated list of the SSL2 ciphers to be used. Ciphers not explicitly listed will be disabled for the target, even if those ciphers are available in the particular cipher suite you are using. If this option is not used, all supported ciphers are assumed to be enabled. Allowed values are:

- `rc4`
- `rc4export`
- `rc2`
- `rc2export`

- idea
- des
- desede3

#### --ssl3enabled

Set this property to `false` to disable SSL3. The default value is `true`. If both SSL2 and SSL3 are enabled for a virtual server, the server tries SSL3 encryption first. In the event SSL3 encryption fails, the server then tries SSL2 encryption.

#### --tlseenabled

Set this property to `false` to disable TLS. The default value is `true`. It is good practice to enable TLS, which is a more secure version of SSL.

#### --ssl3tlsciphers

A comma-separated list of the SSL3 and/or TLS ciphers to be used. Ciphers not explicitly listed will be disabled for the target, even if those ciphers are available in the particular cipher suite you are using. If this option is not used, all supported ciphers are assumed to be enabled. Allowed values are:

- `SSL_RSA_WITH_RC4_128_MD5`
- `SSL_RSA_WITH_3DES_EDE_CBC_SHA`
- `SSL_RSA_WITH_DES_CBC_SHA`
- `SSL_RSA_EXPORT_WITH_RC4_40_MD5`
- `SSL_RSA_WITH_NULL_MD5`
- `SSL_RSA_WITH_RC4_128_SHA`
- `SSL_RSA_WITH_NULL_SHA`

#### --tlsrollbackenabled

Set to `true` (default) to enable TLS rollback. TLS rollback should be enabled for Microsoft Internet Explorer 5.0 and 5.5. This option is only valid when `-tlseenabled=true`.

#### --clientauthenabled

Set to `true` if you want SSL3 client authentication performed on every request independent of ACL-based access control. Default value is `false`.

## Operands

### listener\_id

The ID of the HTTP or IIOP listener for which the SSL element is to be created. The `listener_id` is not required if the `--type` is `iiop-service`.

# Examples

## Example 1 Creating an SSL element for an HTTP listener

The following example shows how to create an SSL element for an HTTP listener named `http-listener-1`.

```
asadmin> create-ssl  
--type http-listener  
--certname sampleCert http-listener-1  
Command create-ssl executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-ssl\(1\)](#)

# create-system-properties

Adds one or more system property elements that can be referenced elsewhere in the configuration.

## Synopsis

```
asadmin [asadmin-options] create-system-properties [--help]
[--target target]
[name=value)[:name=value]*]
```

## Description

The **create-system-properties** subcommand adds or updates system properties that can be referenced elsewhere on the server.

Eclipse GlassFish provides hooks where tokens (system properties) can be specified. Because Eclipse GlassFish does not have multiple server elements, you can specify a particular token at any level. When a domain supports multiple servers, the override potential can be exploited. When a domain is started or restarted, all **<system-property>** elements are resolved and available to the Java Virtual Machine by using the **System.setProperty()** call on each of them (with its name and value derived from the corresponding attributes of the element). This is analogous to sending the elements as **-D** parameters on the Java command line.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

The target on which you are creating the system properties.

## Operands

### target

The valid targets for this subcommand are instance, cluster, configuration, domain, and server.

Server is the default option. Valid values are:

**server**

Creates the properties on the default server instance. This is the default value.

**domain**

Creates the properties for all server instances in the default domain.

**configuration\_name**

Creates the properties in the specified configuration.

**cluster\_name**

Creates the properties on all server instances in the specified cluster.

**instance\_name**

Creates the properties on a specified server instance.

**name=value**

The name value pairs of the system properties to add to the specified target. Multiple system properties must be separated by a : (colon). If a : (colon) appears in the name or value of a system property, it must be escaped with a \ (backslash). If any system properties were previously defined, they are updated with the new values.

## Examples

### Example 1 Creating System Properties

This example creates a system property associated with an HTTP listener on a server instance named `myserver`.

```
asadmin> create-system-properties --target myserver http-listener-port=1088
Command create-system-properties executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[delete-system-property\(1\)](#), [list-system-properties\(1\)](#)

# create-threadpool

Adds a thread pool

## Synopsis

```
asadmin [asadmin-options] create-threadpool [--help]
[--target target]
[--maxthreadpools maxthreadpools]
[--minthreadpools minthreadpools]
[--idletimeout idletimeout] [--maxqueuesize maxqueuesize]
[--workqueues workqueues] threadpool-id
```

## Description

The **create-threadpool** subcommand creates a thread pool with the specified name. You can specify maximum and minimum number of threads in the pool, the quantity of messages, and the idle timeout of a thread. The created thread pool can be used for servicing IIOP requests and for resource adapters to service work management requests. A thread pool can be used in multiple resource adapters.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This option specifies the target on which you are creating the thread pool. Valid values are as follows:

**server**

Creates the thread pool for the default Eclipse GlassFish instance **server** and is the default value

**configuration-name**

Creates the thread pool for the named configuration.

**cluster-name**

Creates the thread pool for every instance in the cluster.

**instance-name**

Creates the thread pool for a particular instance.

**--maxthreadpoolsize**

Specifies the maximum number of threads the pool can contain. Default is 5.

**--minthreadpoolsize**

Specifies the minimum number of threads in the pool. These are created when the thread pool is instantiated. Default is 2.

**--idletimeout**

Specifies the amount of time in seconds after which idle threads are removed from the pool. Default is 900.

**--maxqueuesize**

Specifies the maximum number of messages that can be queued until threads are available to process them for a network listener or IIOP listener. A value of -1 specifies no limit. Default is 4096.

**--workqueues**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

**threadpool-id**

An ID for the work queue, for example, `threadpool-1`.

## Examples

### Example 1 Creating a Thread Pool

This command creates a new thread pool called `threadpool-1`.

```
asadmin> create-threadpool --maxthreadpoolsize 100
--minthreadpoolsize 20 --idletimeout 2 threadpool-1
Command create-threadpool executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-threadpool\(1\)](#), [list-threadpools\(1\)](#)

# create-transport

Adds a new transport

## Synopsis

```
asadmin [asadmin-options] create-transport [--help]
[--acceptorthreads acceptor-threads]
[--buffersizebytes buffer-size]
[--bytebuffertype byte-buffer-type]
[--classname class-name]
[--displayconfiguration={false|true}]
[--enablesnoop={false|true}]
[--idlekeytimeoutseconds idle-key-timeout]
[--maxconnectionscount max-connections]
[--readtimeoutmillis read-timeout]
[--writetimeoutmillis write-timeout]
[--selectionkeyhandler selection-key-handler]
[--selectorpolltimeoutmillis selector-poll-timeout]
[--tcpnodelay={false|true}]
[--target target]
transport-name
```

## Description

The `create-transport` subcommand creates a transport for a network listener. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --acceptorthreads

The number of acceptor threads for the transport. The recommended value is the number of processors in the machine. The default value is `1`.

**--buffersizebytes**

The size, in bytes, of the buffer to be provided for input streams created by the network listener that references this transport. The default value is **8192**.

**--bytebuffertype**

The type of the buffer to be provided for input streams created by a network-listener. Allowed values are **HEAP** and **DIRECT**. The default value is **HEAP**.

**--classname**

The fully qualified name of the Java class that implements the transport. The default is **org.glassfish.grizzly.TCPSelectorHandler**.

**--displayconfiguration**

If **true**, flushes the internal network configuration to the server log. Useful for debugging, but reduces performance. The default is **false**.

**--enablesnoop**

If **true**, writes request/response information to the server log. Useful for debugging, but reduces performance. The default is **false**.

**--idlekeytimeoutseconds**

The idle key timeout. The default is **30** seconds.

**--maxconnectionscount**

The maximum number of connections for the network listener that references this transport. A value of **-1** specifies no limit. The default value is **4096**.

**--readtimeoutmillis**

The amount of time the server waits during the header and body parsing phase. The default is **30000** milliseconds, or 30 seconds.

**--writetimeoutmillis**

The amount of time the server waits before considering the remote client disconnected when writing the response. The default is **30000** milliseconds, or 30 seconds.

**--selectionkeyhandler**

The name of the selection key handler associated with this transport. There is no default.

**--selectorpolltimeoutmillis**

The number of milliseconds a NIO Selector blocks waiting for events (user requests). The default value is **1000** milliseconds.

**--tcpnodelay**

If **true**, the default, enables **TCP\_NODELAY** (also called Nagle's algorithm). The default is **false**.

**--target**

Creates the transport only on the specified target. Valid values are as follows:

**server**

Creates the transport on the default server instance. This is the default value.

**configuration-name**

Creates the transport in the specified configuration.

**cluster-name**

Creates the transport on all server instances in the specified cluster.

**standalone-instance-name**

Creates the transport on the specified standalone server instance.

## Operands

**transport-name**

The name of the transport.

## Examples

### Example 1 Creating a Transport

The following command creates a transport named `http1-trans` that uses a non-default number of acceptor threads:

```
asadmin> create-transport --acceptorthreads 100 http1-trans
Command create-transport executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-network-listener\(1\)](#), [delete-transport\(1\)](#), [list-transports\(1\)](#)

# create-virtual-server

Creates the named virtual server

## Synopsis

```
asadmin [asadmin-options] create-virtual-server [--help]
--hosts hosts
[--httplisteners http-listeners]
[--networklisteners network-listeners]
[--defaultwebmodule default-web-module]
[--state={on|off}]
[--logfile log-file]
[--property (name=value)[:name=value]*]
[--target target]
virtual-server-id
```

## Description

The `create-virtual-server` subcommand creates the named virtual server. Virtualization in the Eclipse GlassFish allows multiple URL domains to be served by a single HTTP server process that is listening on multiple host addresses. If the application is available at two virtual servers, they still share the same physical resource pools.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --hosts

A comma-separated (,) list of values allowed in the host request header to select the current virtual server. Each virtual server that is configured to the same connection group must have a unique host for that group.

#### --httplisteners

A comma-separated (,) list of HTTP listener IDs. Required only for a virtual server that is not the

default virtual server. HTTP listeners are converted to network listeners. This option is deprecated but maintained for backward compatibility. Use `--networklisteners` instead. If `--networklisteners` is used, this option is ignored.

#### **--networklisteners**

A comma-separated (,) list of network listener IDs. Required only for a virtual server that is not the default virtual server.

#### **--defaultwebmodule**

The standalone web module associated with this virtual server by default.

#### **--state**

Determines whether a virtual server is active (`on`) or inactive (`off` or disabled). Default is `on`. When inactive, the virtual server does not service requests.

#### **--logfile**

Name of the file where log entries for this virtual server are to be written. By default, this is the server log. The file and directory in which the access log is kept must be writable by the user account under which the server runs.

#### **--property**

Optional property name/value pairs for configuring the virtual server. The following properties are available:

##### **sso-max-inactive-seconds**

Specifies the number of seconds after which a user's single sign-on record becomes eligible for purging if no client activity is received. Since single sign-on applies across several applications on the same virtual server, access to any of the applications keeps the single sign-on record active. The default value is 300 seconds (5 minutes). Higher values provide longer single sign-on persistence for users, but at the expense of more memory use on the server.

##### **sso-reap-interval-seconds**

Specifies the number of seconds between purges of expired single sign-on records. The default value is 60.

##### **setCacheControl**

Specifies a comma-separated list of `Cache-Control` response directives. For a list of valid directives, see section 14.9 of the document at <http://www.ietf.org/rfc/rfc2616.txt> (<http://www.ietf.org/rfc/rfc2616.txt>).

##### **allowLinking**

If the value of this property is `true`, resources that are symbolic links will be served for all web applications deployed on this virtual server. Individual web applications may override this setting by using the property `allowLinking` under the `sun-web-app` element in the `sun-web.xml` file:

```
<sun-web-app>
<property name="allowLinking" value="[true|false]" />
</sun-web-app>
```

The default value is `true`.

#### **accessLogWriteInterval**

Indicates the number of seconds before the log will be written to the disk. The access log is written when the buffer is full or when the interval expires. If the value is 0 (zero), then the buffer is always written even if it is not full. This means that each time the server is accessed, the log message is stored directly to the file.

#### **accessLogBufferSize**

Specifies the size, in bytes, of the buffer where access log calls are stored.

#### **allowRemoteAddress**

This is a comma-separated list of regular expression patterns to which the remote client's IP address is compared. If this property is specified, the remote address must match for this request to be accepted. If this property is not specified, all requests will be accepted unless the remote address matches a `denyRemoteAddress` pattern. The default value for this property is null.

#### **denyRemoteAddress**

This is a comma-separated list of regular expression patterns to which the remote client's IP address is compared. If this property is specified, the remote address must not match for this request to be accepted. If this property is not specified, request acceptance is governed solely by the `allowRemoteAddress` property. The default value for this property is null.

#### **allowRemoteHost**

This is a comma-separated list of regular expression patterns to which the remote client's host name (as returned by `java.net.Socket.getInetAddress().getHostName()`) is compared. If this property is specified, the remote host name must match for this request to be accepted. If this property is not specified, all requests will be accepted unless the remote host name matches a `denyRemoteHost` pattern. The default value for this property is null.

#### **denyRemoteHost**

This is a comma-separated list of regular expression patterns to which the remote client's host name (as returned by `java.net.Socket.getInetAddress().getHostName()`) is compared. If this property is specified, the remote host name must not match for this request to be accepted. If this property is not specified, request acceptance is governed solely by the `allowRemoteHost` property. The default value for this property is null.

#### **authRealm**

Specifies the `name` attribute of an `auth-realm`, which overrides the server instance's default realm for standalone web applications deployed to this virtual server. A realm defined in a standalone

web application's `web.xml` file overrides the virtual server's realm.

#### **securePagesWithPragma**

Set this property to `false` to ensure that for all web applications on this virtual server file downloads using SSL work properly in Internet Explorer.

You can set this property for a specific web application. For details, see "[glassfish-web-app](#)" in Eclipse GlassFish Application Deployment Guide.

#### **contextXmlDefault**

Specifies the location, relative to domain-dir, of the `context.xml` file for this virtual server, if one is used. For more information about the `context.xml` file, see "[Using a context.xml File](#)" in Eclipse GlassFish Application Development Guide and The Context Container (<http://tomcat.apache.org/tomcat-5.5-doc/config/context.html>). Context parameters, environment entries, and resource definitions in `context.xml` are supported in the Eclipse GlassFish.

#### **alternatedocroot\_n**

Specifies an alternate document root (docroot), where n is a positive integer that allows specification of more than one. Alternate docroots allow web applications to serve requests for certain resources from outside their own docroot, based on whether those requests match one (or more) of the URI patterns of the web application's alternate docroots.

If a request matches an alternate docroot's URI pattern, it is mapped to the alternate docroot by appending the request URI (minus the web application's context root) to the alternate docroot's physical location (directory). If a request matches multiple URI patterns, the alternate docroot is determined according to the following precedence order:

- Exact match
- Longest path match
- Extension match

For example, the following properties specify three alternate docroots. The URI pattern of the first alternate docroot uses an exact match, whereas the URI patterns of the second and third alternate docroots use extension and longest path prefix matches, respectively.

```
<property name="alternatedocroot_1"
  value="from=/my.jpg dir=/srv/images/jpg"/>
<property name="alternatedocroot_2"
  value="from=*.jpg dir=/srv/images/jpg"/>
<property name="alternatedocroot_3"
  value="from=/jpg/* dir=/src/images"/>
```

The `value` of each alternate docroot has two components: The first component, `from`, specifies the alternate docroot's URI pattern, and the second component, `dir`, specifies the alternate docroot's physical location (directory). Spaces are allowed in the `dir` component.

You can set this property for a specific web application. For details, see "[glassfish-web-app](#)" in

## Eclipse GlassFish Application Deployment Guide.

### **send-error\_n**

Specifies custom error page mappings for the virtual server, which are inherited by all web applications deployed on the virtual server. A web application can override these custom error page mappings in its `web.xml` deployment descriptor. The value of each `send-error_n` property has three components, which may be specified in any order:

- The first component, `code`, specifies the three-digit HTTP response status code for which the custom error page should be returned in the response.
- The second component, `path`, specifies the absolute or relative file system path of the custom error page. A relative file system path is interpreted as relative to the domain-dir/`config` directory.
- The third component, `reason`, is optional and specifies the text of the reason string (such as `Unauthorized` or `Forbidden`) to be returned.

For example:

```
<property name="send-error_1"
  value="code=401 path=/myhost/401.html reason=MY-401-REASON"/>
```

This example property definition causes the contents of `/myhost/401.html` to be returned with 401 responses, along with this response line:

```
HTTP/1.1 401 MY-401-REASON
```

### **redirect\_n**

Specifies that a request for an old URL is treated as a request for a new URL. These properties are inherited by all web applications deployed on the virtual server. The value of each `redirect_n` property has two components, which may be specified in any order:

- The first component, `from`, specifies the prefix of the requested URI to match.
- The second component, `url-prefix`, specifies the new URL prefix to return to the client. The `from` prefix is simply replaced by this URL prefix.

For example:

```
<property name="redirect_1" value="from=/dummy url-prefix=http://etude"/>
```

### **valve\_n**

Specifies a fully qualified class name of a custom valve, where n is a positive integer that allows

specification of more than one. The valve class must implement the `org.apache.catalina.Valve` interface from Tomcat or previous Eclipse GlassFish releases, or the `org.glassfish.web.valve.GlassFishValve` interface from the current Eclipse GlassFish release. For example:

```
<property name="valve_1" value="org.glassfish.extension.Valve"/>
```

You can set this property for a specific web application. For details, see "[glassfish-web-app](#)" in Eclipse GlassFish Application Deployment Guide.

#### **listener\_n**

Specifies a fully qualified class name of a custom Catalina listener, where n is a positive integer that allows specification of more than one. The listener class must implement the `org.apache.catalina.ContainerListener` or `org.apache.catalina.LifecycleListener` interface. For example:

```
<property name="listener_1"
  value="org.glassfish.extension.MyLifecycleListener"/>
```

You can set this property for a specific web application. For details, see "[glassfish-web-app](#)" in Eclipse GlassFish Application Deployment Guide.

#### **docroot**

Absolute path to root document directory for server. Deprecated. Replaced with a `virtual-server` attribute, `docroot`, that is accessible using the `get`, `set`, and `list` subcommands.

#### **accesslog**

Absolute path to server access logs. Deprecated. Replaced with a `virtual-server` attribute , `access-log`, that is accessible using the `get`, `set`, and `list` subcommands.

#### **accessLoggingEnabled**

If `true`, access logging is enabled for this virtual server. Deprecated. Replaced with a `virtual-server` attribute, `access-logging-enabled`, that is accessible using the `get`, `set`, and `list` subcommands.

#### **sso-enabled**

If `true`, single sign-on is enabled for web applications on this virtual server that are configured for the same realm. Deprecated. Replaced with a `virtual-server` attribute, `sso-enabled`, that is accessible using the `get`, `set`, and `list` subcommands.

#### **ssoCookieSecure**

Sets the `Secure` attribute of any `JSESSIONIDSSO` cookies associated with the web applications deployed to this virtual server. Deprecated. Replaced with a `virtual-server` attribute, `sso-cookie-`

**secure**, that is accessible using the **get**, **set**, and **list** subcommands.

#### **errorReportValve**

Specifies a fully qualified class name of a custom valve that produces default error pages for applications on this virtual server. Specify an empty string to disable the default error page mechanism for this virtual server.

#### **--target**

Creates the virtual server only on the specified target. Valid values are as follows:

##### **server**

Creates the virtual server on the default server instance. This is the default value.

##### **configuration-name**

Creates the virtual server in the specified configuration.

##### **cluster-name**

Creates the virtual server on all server instances in the specified cluster.

##### **standalone-instance-name**

Creates the virtual server on the specified standalone server instance.

## Operands

### **virtual-server-id**

Identifies the unique ID for the virtual server to be created. This ID cannot begin with a number.

## Examples

### Example 1 Creating a Virtual Server

The following command creates a virtual server named **sampleServer**:

```
asadmin> create-virtual-server --hosts pigeon,localhost  
--property authRealm=ldap sampleServer  
Command create-virtual-server executed successfully.
```

## Exit Status

**0**

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[delete-virtual-server\(1\)](#), [list-virtual-servers\(1\)](#), [create-http-listener\(1\)](#), [create-network-listener\(1\)](#)

[get\(1\)](#), [list\(1\)](#), [set\(1\)](#)

# delete-admin-object

Removes the administered object with the specified JNDI name.

## Synopsis

```
asadmin [asadmin-options] delete-admin-object [--help]
[--target target] jndi_name
```

## Description

The **delete-admin-object** subcommand removes an administered object with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This is the name of the targets for which the administered object is to be deleted. Valid values are:



Resources are always created for a domain as a whole but are only active for targets for which a `<resource-ref>` has been created using the **--target** option when the resource was created. This means that deleting a resource only deletes the `<resource-ref>` element for the specified **--target**, and does not delete the resource from the domain as a whole unless `domain` is specified as the **--target** for the deletion.

### server

Deletes the administered object for the default server instance `server` and is the default value.

### configuration\_name

Deletes the administered object for the specified configuration.

**cluster\_name**

Deletes the administered object for the specified cluster.

**instance\_name**

Deletes the administered object for a particular server instance.

## Operands

**jndi\_name**

JNDI name of the administered object to be deleted.

## Examples

### Example 1 Deleting an Administered Object

This example deletes the administered object named `jms/samplequeue`.

```
asadmin> delete-admin-object jms/samplequeue
Command delete-admin-object executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-admin-object\(1\)](#), [list-admin-objects\(1\)](#)

# delete-application-ref

Removes a reference to an application

## Synopsis

```
asadmin [asadmin-options] delete-application-ref [--help]
[--target target]
[--cascade=false] reference_name
```

## Description

The **delete-application-ref** subcommand removes a reference from a cluster or an unclustered server instance to an application. This effectively results in the application element being undeployed and no longer available on the targeted instance or cluster.

The target instance or instances making up the cluster need not be running or available for this subcommand to succeed. If one or more instances are not available, they will no longer load the application the next time they start.

Removal of the reference does not result in removal of the application from the domain. The bits are removed only by the **undeploy** subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --target

Specifies the target from which you are removing the application reference. Valid values are

- **server** - Specifies the default server instance as the target.  
**server** is the name of the default server instance and is the default value.
- **cluster\_name** - Specifies a certain cluster as the target.
- **instance\_name** - Specifies a certain stand-alone server instance as the target.

**--cascade**

For a connector module, indicates whether the resources dependent on the module should also be recursively deleted. The default is `false`. The connector module can be either a stand-alone RAR file or a module within an EAR file.

## Operands

**reference\_name**

The name of the application or module, which can be a Jakarta EE application module, Web module, EJB module, connector module, application client module, or lifecycle module.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. To delete references to multiple versions, you can use an asterisk (\*) as a wildcard character. For more information about module and application versions, see "[Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

## Examples

### Example 1 Deleting an Application Reference

The following example removes a reference to the Web module `MyWebApp` from the unclustered server instance `NewServer`.

```
asadmin> delete-application-ref --target NewServer MyWebApp
Command delete-application-ref executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)[create-application-ref\(1\)](#), [list-application-references\(1\)](#), [undeploy\(1\)](#)

## Eclipse GlassFish Application Deployment Guide

# delete-audit-module

Removes the named audit-module

## Synopsis

```
asadmin [asadmin-options] delete-audit-module [--help]
[--target target]
audit_module_name
```

## Description

This subcommand removes the named audit module. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target on which you are deleting the audit module. Valid values are as follows:

**server**

Deletes the audit module for the default server instance `server` and is the default value.

**configuration\_name**

Deletes the audit module for the named configuration.

**cluster\_name**

Deletes the audit module for every server instance in the cluster.

**instance\_name**

Deletes the audit module for a particular server instance.

# Operands

## **audit\_module\_name**

The name of the audit module to be deleted.

## Examples

### Example 1 Deleting an audit module

```
asadmin> delete-audit-module sampleAuditModule  
Command delete-audit-module executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-audit-module\(1\)](#), [list-audit-modules\(1\)](#)

# delete-auth-realm

Removes the named authentication realm

## Synopsis

```
asadmin [asadmin-options] delete-auth-realm [--help]
[--target target]
auth_realm-name
```

## Description

The **delete-auth-realm** subcommand removes the named authentication realm. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target on which you are deleting the authentication realm. Valid values are

**server**

Deletes the realm for the default server instance **server** and is the default value.

**configuration\_name**

Deletes the realm for the named configuration.

**cluster\_name**

Deletes the realm for every server instance in the cluster.

**instance\_name**

Deletes the realm for a particular server instance.

# Operands

## **auth\_realm\_name**

Name of the realm to be deleted.

# Examples

## Example 1 Deleting an Authentication Realm

This example deletes the authentication realm **db**.

```
asadmin> delete-auth-realm db
Command delete-auth-realm executed successfully
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-auth-realm\(1\)](#), [list-auth-realms\(1\)](#)

# delete-cluster

Deletes a Eclipse GlassFish cluster

## Synopsis

```
asadmin [asadmin-options] delete-cluster [--help]
[--autohadboverride={true|false}] [--node-agent=node-agent--name]
cluster-name
```

## Description

The **delete-cluster** subcommand deletes a Eclipse GlassFish cluster. A cluster can be deleted only if the cluster contains no Eclipse GlassFish instances. If a cluster that you are deleting contains any instances, stop and delete the instances before deleting the cluster.

If the cluster's named configuration was created automatically for the cluster and no other clusters or unclustered instances refer to the configuration, the configuration is deleted when the cluster is deleted. A configuration that is created automatically for a cluster is named `cluster-name`-config``, where `cluster-name` is the name of the cluster.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --autohadboverride

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

#### --nodeagent

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

# Operands

## cluster-name

The name of the cluster to delete.

## Examples

### Example 1 Deleting a Eclipse GlassFish Cluster

This example deletes the Eclipse GlassFish cluster `adccluster`.

```
asadmin> delete-cluster adccluster
Command delete-cluster executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-cluster\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [list-clusters\(1\)](#), [start-cluster\(1\)](#),  
[stop-instance\(1\)](#), [stop-local-instance\(1\)](#), [stop-cluster\(1\)](#)

# delete-config

Deletes an existing named configuration

## Synopsis

```
asadmin [asadmin-options] delete-config [--help]
configuration-name
```

## Description

The **delete-config** subcommand deletes an existing named configuration from the configuration of the domain administration server (DAS). You can delete a configuration only if no Eclipse GlassFish instances or clusters refer to the configuration. A standalone configuration is automatically deleted when the instance or cluster that refers to it is deleted. You cannot delete the **default-config** configuration that is copied to create standalone configurations.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### configuration-name

The name of the configuration that you are deleting.

## Examples

### Example 1 Deleting a Named Configuration

This example deletes the named configuration **pmdconfig**.

```
asadmin> delete-config pmdconfig
```

Command delete-config executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[copy-config\(1\), list-configs\(1\)](#)

[configuration\(5ASC\)](#)

# delete-connector-connection-pool

Removes the specified connector connection pool

## Synopsis

```
asadmin [asadmin-options] delete-connector-connection-pool [--help]
[--target target]
[--cascade={false|true}] poolname
```

## Description

The **delete-connector-connection-pool** subcommand removes the specified connector connection pool.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

#### --cascade

When set to true, all connector resources associated with the pool, and the pool itself, are deleted. When set to false, the deletion of pool fails if any resources are associated with the pool. The resource must be deleted explicitly or the option must be set to true. Default is false.

## Operands

### poolname

The name of the connection pool to be removed.

# Examples

## Example 1 Deleting a Connector Connection Pool

This example deletes the connector connection pool named `jms/qConnPool`.

```
asadmin> delete-connector-connection-pool  
--cascade=false jms/qConnPool  
Command delete-connector-connection-pool executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-connection-pool\(1\)](#), [list-connector-connection-pools\(1\)](#), [ping-connection-pool\(1\)](#)

# delete-connector-resource

Removes the connector resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] delete-connector-resource [--help]
[--target target] jndi_name
```

## Description

The **delete-connector-resource** subcommand removes the connector resource with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target from which you want to remove the connector resource. Valid targets are:



Resources are always created for a domain as a whole but are only active for targets for which a <resource-ref> has been created using the **--target** option when the resource was created. This means that deleting a resource only deletes the <resource-ref> element for the specified **--target**, and does not delete the resource from the domain as a whole unless **domain** is specified as the **--target** for the deletion.

#### server

Deletes the connector resource from the default server instance. This is the default value.

#### domain

Deletes the connector resource from the domain.

**cluster\_name**

Deletes the connector resource from every server instance in the cluster.

**instance\_name**

Deletes the connector resource from a specified server instance.

# Operands

**jndi\_name**

The JNDI name of this connector resource.

# Examples

## Example 1 Deleting a Connector Resource

This example deletes a connector resource named `jms/qConnFactory`.

```
asadmin> delete-connector-resource jms/qConnFactory
Command delete-connector-resource executed successfully
```

## Example 2 Using the delete-connector-resource subcommand

This example shows the usage of this subcommand.

```
asadmin> delete-connector-resource jms/qConnFactory
Command delete-connector-resource executed successfully
```

Where `jms/qConnFactory` is the connector resource that is removed.

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-resource\(1\)](#), [list-connector-resources\(1\)](#)

# delete-connector-security-map

Deletes a security map for the specified connector connection pool

## Synopsis

```
asadmin [asadmin-options] delete-connector-security-map [--help]
--poolname connector_connection_pool_name [--target target] mapname
```

## Description

The **delete-connector-security-map** subcommand deletes a security map for the specified connector connection pool.

For this subcommand to succeed, you must have first created a connector connection pool using the **create-connector-connection-pool** subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the **asadmin(1M)** help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --poolname

Specifies the name of the connector connection pool to which the security map that is to be deleted belongs.

#### --target

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

### mapname

Name of the security map to be deleted.

# Examples

## Example 1 Deleting a Connector Security Map

This example deletes `securityMap1` for the existing connection pool named `connector-pool1`.

```
asadmin> delete-connector-security-map  
--poolname connector-pool1 securityMap1  
Command delete-connector-security-map executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-security-map\(1\)](#), [list-connector-security-maps\(1\)](#), [update-connector-security-map\(1\)](#)

# delete-connector-work-security-map

Deletes a work security map for the specified resource adapter

## Synopsis

```
asadmin [asadmin-options] delete-connector-work-security-map [--help]
--rname rname
mapname
```

## Description

The **delete-connector-work-security-map** subcommand deletes a security map associated with the specified resource adapter. For this subcommand to succeed, you must have first created and deployed the specified resource adapter.

The enterprise information system (EIS) is any system that holds the data of an organization. It can be a mainframe, a messaging system, a database system, or an application.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --rname

Indicates the connector module name with which the work security map is associated.

## Operands

### mapname

The name of the work security map to be deleted.

## Examples

## Example 1 Deleting a Connector Work Security Map

This example deletes the work security map named `work_security_map_name` for the resource adapter named `ra_name`.

```
asadmin delete-connector-work-security-map  
--rname ra_name work_security_map_name  
Command delete-connector-work-security-map executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-work-security-map\(1\)](#), [list-connector-work-security-maps\(1\)](#), [update-connector-work-security-map\(1\)](#)

# delete-context-service

Removes a context service resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] delete-context-service [--help]
[--target target]
context-service-name
```

## Description

The **delete-context-service** subcommand removes a context service resource with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target from which you are deleting the resource. Valid targets are:

##### server

Deletes the resource from the default server instance. This is the default value.

##### domain

Deletes the resource from the domain.

##### cluster-name

Deletes the resource from every server instance in the specified cluster.

##### instance-name

Deletes the resource from the specified server instance.

# Operands

## context-service-name

The JNDI name of the resource to be deleted.

# Examples

## Example 1 Deleting a Context Service Resource

This example deletes the context service resource named `concurrent/myContextService`.

```
asadmin> delete-context-service concurrent/myContextService
Context service concurrent/myContextService deleted successfully.
Command delete-context-service executed successfully.
```

# Exit Status

0

command executed successfully

1

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-context-service\(1\)](#), [list-context-services\(1\)](#)

# delete-custom-resource

Removes a custom resource

## Synopsis

```
asadmin [asadmin-options] delete-custom-resource [--help]
[--target target] jndi-name
```

## Description

The `delete-custom-resource` subcommand removes a custom resource.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This option helps specify the location of the custom resources that you are deleting. Valid targets are server, domain, cluster, and instance. The default is server.



Resources are always created for a domain as a whole but are only active for targets for which a `<resource-ref>` has been created using the `--target` option when the resource was created. This means that deleting a resource only deletes the `<resource-ref>` element for the specified `--target`, and does not delete the resource from the domain as a whole unless `domain` is specified as the `--target` for the deletion.

**server**

Deletes the resource for the default server instance. This is the default value.

**domain**

Deletes the resource for the domain.

**cluster\_name**

Deletes the resource for every server instance in the cluster.

**instance\_name**

Deletes the resource for a particular server instance.

## Operands

**jndi-name**

The JNDI name of this resource.

## Examples

### Example 1 Deleting a Custom Resource

This example deletes a custom resource named `mycustomresource`.

```
asadmin> delete-custom-resource mycustomresource
Command delete-custom-resource executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-custom-resource\(1\)](#), [list-custom-resources\(1\)](#)

# delete-domain

Deletes a domain

## Synopsis

```
asadmin [asadmin-options] delete-domain [--help]
[--domaindir domaindir] domain-name
```

## Description

The **delete-domain** subcommand deletes the specified domain. The domain must already exist and must be stopped.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --domaindir

The directory where the domain to be deleted is located. If specified, the path must be accessible in the file system. If not specified, the domain under the domain root directory, which defaults to `as-install/domains`, is deleted.

## Operands

### domain-name

The unique name of the domain you want to delete.

## Examples

## Example 1 Deleting a Domain

This example deletes a domain named `mydomain4` from the default domains directory.

```
asadmin> delete-domain mydomain4
Domain mydomain4 deleted.
Command delete-domain executed successfully.
```

## Example 2 deleting a Domain From an Alternate Location

This example deletes a domain named `sampleDomain` from the `/home/someuser/domains` directory.

```
asadmin> delete-domain --domaindir /home/someuser/domains sampleDomain
Domain sampleDomain deleted
Command delete-domain executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-domain\(1\)](#), [list-domains\(1\)](#), [start-domain\(1\)](#), [stop-domain\(1\)](#)

# delete-file-user

Removes the named file user

## Synopsis

```
asadmin [asadmin-options] delete-file-user [--help]
[--authrealmname auth_realm_name]
[--target target]
username
```

## Description

The **delete-file-user** subcommand deletes the entry in the keyfile for the specified username.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --authrealmname

The name of the authentication realm with which the user was created.

#### --target

This is the name of the target on which the command operates. The valid targets are:

##### server

Deletes the file user on the default server instance. This is the default value

##### domain

Deletes the file user in the domain.

##### cluster\_name

Deletes the file user from every server instance in the cluster.

##### instance\_name

Deletes the file user from a particular server instance.

# Operands

## username

This is the name of file user to be deleted.

## Examples

### Example 1 Deleting a User From a File Realm

The following example shows how to delete user named `sample_user` from a file realm.

```
asadmin> delete-file-user  
sample_user  
Command delete-file-user executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-file-user\(1\)](#), [list-file-groups\(1\)](#), [list-file-users\(1\)](#), [update-file-user\(1\)](#)

# delete-http

Removes HTTP parameters from a protocol

## Synopsis

```
asadmin [asadmin-options] delete-http [--help]
[--target target]
protocol-name
```

## Description

The `delete-http` subcommand removes the specified HTTP parameter set from a protocol. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Deletes the HTTP parameter set only from the specified target. Valid values are as follows:

##### server

Deletes the HTTP parameter set from the default server instance. This is the default value.

##### configuration-name

Deletes the HTTP parameter set from the specified configuration.

##### cluster-name

Deletes the HTTP parameter set from all server instances in the specified cluster.

##### standalone-instance-name

Deletes the HTTP parameter set from the specified standalone server instance.

# Operands

## protocol-name

The name of the protocol from which to delete the HTTP parameter set.

## Examples

### Example 1 Deleting an HTTP Parameter Set

The following command deletes the HTTP parameter set from a protocol named `http-1`:

```
asadmin> delete-http http-1
Command delete-http executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-http\(1\)](#)

# delete-http-health-checker

Deletes the health-checker for a specified load balancer configuration

## Synopsis

```
asadmin [asadmin-options] delete-http-health-checker [--help]
[--config config_name]
target
```

## Description

The `delete-http-health-checker` subcommand deletes the health checker from a load balancer configuration. A health checker is unique for the combination of target and load balancer configuration.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--config`

The load balancer configuration from which you delete the health-checker.

## Operands

### target

Specifies the target from which you are deleting the health checker.

Valid values are:

- `cluster_name` - The name of a target cluster.
- `instance_name` - The name of a target server instance.

# Examples

## Example 1 Deleting a Health Checker from a Load Balancer Configuration

This example deletes the health checker for load balancer configuration named `mycluster-http-lb-config` on a cluster named `mycluster`.

```
asadmin> delete-http-health-checker --user admin  
--passwordfile password.txt --config mycluster-http-lb-config mycluster
```

```
Command delete-http-health-checker executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-health-checker\(1\)](#)

# delete-http-lb

Deletes a load balancer

## Synopsis

```
asadmin [asadmin-options] delete-http-lb [--help]
load_balancer_name
```

## Description

Use the **delete-http-lb** subcommand to delete a physical load balancer.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### load\_balancer\_name

The name of the load balancer to be deleted.

## Examples

### Example 1 Deleting a Load Balancer Configuration

This example deletes the load balancer configuration named **mylb**.

```
asadmin> delete-http-lb mylb  
Command delete-http-lb executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb\(1\)](#), [list-http-lbs\(1\)](#)

# delete-http-lb-config

Deletes a load balancer configuration

## Synopsis

```
asadmin [asadmin-options] delete-http-lb-config [--help]
config_name
```

## Description

Use the **delete-http-lb-config** subcommand to delete a load balancer configuration. The load balancer configuration must not reference any clusters or server instances enabled for load balancing. In addition, the load balancer configuration must not be referenced by any physical load balancers.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### config\_name

The name of the load balancer configuration to delete. The configuration must not reference any clusters or server instances enabled for load balancing, or be used by any physical load balancers.

## Examples

### Example 1 Deleting a Load Balancer Configuration

This example deletes a load balancer configuration named **mylbconfig**

```
asadmin> delete-http-lb-config mylbconfig
Command delete-http-lb-config executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb-config\(1\)](#), [list-http-lb-configs\(1\)](#)

# delete-http-lb-ref

Deletes the cluster or server instance from a load balancer

## Synopsis

```
asadmin [asadmin-options] delete-http-lb-ref [--help]
--config config_name | --lbname load_balancer_name
[--force=false] target
```

## Description

Use the **delete-http-lb-ref** subcommand to remove a reference to a cluster or standalone server instance from a load balancer configuration or load balancer. So that you do not interrupt user requests, make sure the standalone server instance or all server instances in the cluster are disabled before you remove them from the load balancer configuration. If the **force** option is set to true, the references are deleted even if server instances or clusters are enabled.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --config

Specifies which load balancer configuration to delete cluster and server instance references from. Specify either a load balancer configuration or a load balancer. Specifying both results in an error.

#### --lbname

Specifies the load balancer to delete cluster and server instance references from.

Specify either a load balancer configuration or a load balancer. Specifying both results in an error.

#### --force

If **force** is set to true, then the references are deleted even if there are currently enabled applications or instances. The default is false.

# Operands

## target

Specifies which cluster or instance to remove from the load balancer. Valid values are:

- cluster\_name- The name of a target cluster.
- instance\_name- The name of a target server instance.

## Examples

### Example 1 Deleting a Cluster Reference from a Load Balancer

#### Configuration

This example deletes the reference to cluster named `cluster2` from a load balancer configuration named `mycluster-http-lb-config`.

```
asadmin> delete-http-lb-ref --config mycluster-http-lb-config cluster2
```

```
Command delete-http-lb-ref executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb-ref\(1\)](#), [disable-http-lb-server\(1\)](#)

# delete-http-listener

Removes a network listener

## Synopsis

```
asadmin [asadmin-options] delete-http-listener [--help]
[--target target]
listener-id
```

## Description

The `delete-http-listener` subcommand removes the specified network listener.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Deletes the network listener only from the specified target. Valid values are as follows:

##### server

Deletes the network listener from the default server instance. This is the default value.

##### configuration-name

Deletes the network listener from the specified configuration.

##### cluster-name

Deletes the network listener from all server instances in the specified cluster.

##### standalone-instance-name

Deletes the network listener from the specified standalone server instance.

# Operands

## listener-id

The unique identifier for the network listener to be deleted.

# Examples

## Example 1 Using the delete-http-listener subcommand

The following command deletes the network listener named `sampleListener`:

```
asadmin> delete-http-listener sampleListener
Command delete-http-listener executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-http-listener\(1\)](#), [list-http-listeners\(1\)](#)

# delete-http-redirect

Removes an HTTP redirect

## Synopsis

```
delete-http-redirect [--help]
[--target target]
protocol-name
```

## Description

The `delete-http-redirect` subcommand removes the specified HTTP redirect. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Deletes the HTTP redirect only from the specified target. Valid values are as follows:

**server**

Deletes the HTTP redirect from the default server instance. This is the default value.

**configuration-name**

Deletes the HTTP redirect from the specified configuration.

**cluster-name**

Deletes the HTTP redirect from all server instances in the specified cluster.

**standalone-instance-name**

Deletes the HTTP redirect from the specified standalone server instance.

# Operands

## protocol-name

The name of the associated protocol.

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-http-redirect\(1\)](#)

# delete-iiop-listener

Removes an IIOP listener

## Synopsis

```
delete-iiop-listener [--help] [--target target] listener_id
```

## Description

The `delete-iiop-listener` subcommand removes the specified IIOP listener. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target from which you are deleting the IIOP listener. Valid values are

##### server

Deletes the listener from the default server instance `server` and is the default value.

##### configuration\_name

Deletes the listener from the named configuration.

##### cluster\_name

Deletes the listener from every server instance in the cluster.

##### instance\_name

Deletes the listener from a particular server instance.

## Operands

### listener\_id

The unique identifier for the IIOP listener to be deleted.

# Examples

## Example 1 Deleting an IIOP Listener

The following command deletes the IIOP listener named `sample_iiop_listener`:

```
asadmin> delete-iiop-listener sample_iiop_listener
Command delete-iiop-listener executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-iiop-listener\(1\)](#), [list-iiop-listeners\(1\)](#)

# delete-instance

Deletes a Eclipse GlassFish instance

## Synopsis

```
asadmin [asadmin-options] delete-instance [--help]
instance-name
```

## Description

The **delete-instance** subcommand deletes a Eclipse GlassFish instance. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured on the host where the domain administration server (DAS) is running and on the host that is represented by the node where the instance resides.



DCOM or SSH is not required if the instance resides on a node of type **CONFIG** that represents the local host. A node of type **CONFIG** is not enabled for remote communication over DCOM or SSH.

You may run this subcommand from any host that can contact the DAS.

The subcommand can delete any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can delete an instance that was created by using the [create-local-instance\(1\)](#) subcommand.

The instance that is being deleted must not be running. Otherwise, an error occurs.

The subcommand deletes an instance by performing the following actions:

- Removing the instance from the configuration of the domain administration server (DAS)
- Deleting the instance's files from file system

If the instance that is being deleted is the only instance that is using the node directory, that directory is also removed.

If a standalone instance is deleted, the instance's standalone configuration is also deleted. A standalone instance refers to a configuration that is named `instance-name`-config`` to which no other clusters or unclustered instances refer.

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

# Operands

## instance-name

The name of the instance to delete.

# Examples

## Example 1 Deleting a Eclipse GlassFish Instance

This example deletes the Eclipse GlassFish instance `pmdsainst`.

```
asadmin> delete-instance pmdsainst
Command delete-instance executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-local-instance\(1\)](#), [setup-ssh\(1\)](#), [start-instance\(1\)](#), [start-local-instance\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#), [validate-dcom\(1\)](#)

# delete-jacc-provider

Enables administrators to delete JACC providers defined for a domain

## Synopsis

```
asadmin [asadmin-options] delete-jacc-provider [--help]
[--target target] jacc-provider-name
```

## Description

The `delete-jacc-provider` subcommand enables administrators to delete JACC providers defined for a domain. JACC providers are defined as `jacc-provider` elements in the `security-service` element in the domain's `domain.xml` file. JACC providers can be created using the Eclipse GlassFish Admin Console or the `create-jacc-provider` subcommand.

The default Eclipse GlassFish installation includes two JACC providers, named `default` and `simple`. These default providers should not be deleted.

The JACC provider used by Eclipse GlassFish for authorization is identified by the `jacc-provider` element of `security-service` in `domain.xml`. Therefore, if you delete the `jacc-provider` provider, make sure you change `jacc-provider` to the name of some other JACC provider that exists under `security-service`.

If you change the `jacc-provider` element to point to a different JACC provider, you must restart Eclipse GlassFish.

This subcommand is supported in remote mode only.

## Options

If an option has a short option name, then the short option precedes the long option name. Short options have one dash whereas long options have two dashes.

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--target`

Specifies the target from which you are deleting the JACC provider. The following values are valid:

**server**

Deletes the JACC provider on the default server instance. This is the default value.

**configuration\_name**

Deletes the JACC provider in the specified configuration.

**cluster\_name**

Deletes the JACC provider on all server instances in the specified cluster.

**instance\_name**

Deletes the JACC provider on a specified server instance.

## Operands

**jacc-provider-name**

The name of the JACC provider to be deleted.

## Examples

### Example 1 Deleting a JACC provider

The following example shows how to delete a JACC provider named `testJACC` from the default domain.

```
asadmin> delete-jacc-provider testJACC  
Command delete-jacc-provider executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jacc-provider\(1\)](#), [list-jacc-providers\(1\)](#)



# delete-javamail-resource

Removes a JavaMail session resource

## Synopsis

```
asadmin [asadmin-options] delete-javamail-resource [--help]
[--target target] jndi_name
```

## Description

The **delete-javamail-resource** subcommand removes the specified JavaMail session resource. Ensure that you remove all references to this resource before running this subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target from which you are deleting the JavaMail session resource. Valid values are:

##### server

Deletes the resource from the default server instance. This is the default value.

##### domain

Deletes the resource from the domain.

##### cluster\_name

Deletes the resource from every server instance in the cluster.

##### instance\_name

Deletes the resource from a particular server instance.

# Operands

## jndi\_name

The JNDI name of the JavaMail session resource to be deleted.

## Examples

### Example 1 Deleting a JavaMail Resource

This example deletes the JavaMail session resource named `mail/MyMailSession`.

```
asadmin> delete-javamail-resource mail/MyMailSession
Command delete-javamail-resource executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-javamail-resource\(1\)](#), [list-javamail-resources\(1\)](#)

# delete-jdbc-connection-pool

Removes the specified JDBC connection pool

## Synopsis

```
asadmin [asadmin-options] delete-jdbc-connection-pool [--help]
[--cascade={false|true}]
[--target target]
jdbc_connection_pool_id
```

## Description

The `delete-jdbc-connection-pool` subcommand deletes a JDBC connection pool. Before running this subcommand, all associations to the JDBC connection pool must be removed.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --cascade

If the option is set to true, all the JDBC resources associated with the pool, apart from the pool itself, are deleted. When set to false, the deletion of pool fails if any resources are associated with the pool. Resources must be deleted explicitly or the option must be set to true. The default value is false.

### --target

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

### jdbc\_connection\_pool\_id

The name of the JDBC resource to be removed.

# Examples

## Example 1 Deleting a JDBC Connection Pool

This example deletes the `sample_derby_pool` JDBC connection pool.

```
asadmin> delete-jdbc-connection-pool --cascade=false sample_derby_pool  
Command delete-jdbc-connection-pool executed correctly.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jdbc-connection-pool\(1\)](#), [list-jdbc-connection-pools\(1\)](#)

# delete-jdbc-resource

Removes a JDBC resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] delete-jdbc-resource [--help]
[--target target] jndi_name
```

## Description

The **delete-jdbc-resource** subcommand removes a JDBC resource. Ensure that all associations to the JDBC resource are removed before running this subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option helps specify the target from which you are removing the JDBC resource. Valid targets are:

##### server

Removes the resource from the default server instance. This is the default value.

##### domain

Removes the resource from the domain.

##### cluster\_name

Removes the resource from every server instance in the cluster.

##### instance\_name

Removes the resource from a particular server instance.



Resources are always created for a domain as a whole but are only active for targets for which a <resource-ref> has been created using the --target option when the resource was created. This means that deleting a resource only deletes the <resource-ref> element for the specified --target, and does not delete the resource from the domain as a whole unless domain is specified as the --target for the deletion.

## Operands

### jndi\_name

The JNDI name of this JDBC resource to be removed.

## Examples

### Example 1 Deleting a JDBC Resource

The following example deletes the JDBC resource named `jdbc/DerbyPool`.

```
asadmin> delete-jdbc-resource jdbc/DerbyPool
Command delete-jdbc-resource executed successfully.
```

## Exit Status

0

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jdbc-resource\(1\)](#), [list-jdbc-resources\(1\)](#)

# delete-jmsdest

Removes a JMS physical destination

## Synopsis

```
asadmin [asadmin-options] delete-jmsdest [--help]
--desttype type
[--target target]
dest_name
```

## Description

The `delete-jmsdest` subcommand removes the specified Java Message Service (JMS) physical destination.

This subcommand is supported in remote mode only. Remote `asadmin` subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --desttype

The type of the JMS destination. Valid values are `topic` and `queue`.

#### --target

Deletes the physical destination only from the specified target. Although the `delete-jmsdest` subcommand is related to resources, a physical destination is deleted using the JMS Service (JMS Broker), which is part of the configuration. A JMS Broker is configured in the config section of `domain.xml`. Valid values are as follows:

#### server

Deletes the physical destination from the default server instance. This is the default value.

#### configuration-name

Deletes the physical destination from the specified configuration.

**cluster-name**

Deletes the physical destination from every server instance in the specified cluster.

**instance-name**

Creates the physical destination from the specified server instance.

# Operands

**dest\_name**

The unique identifier of the JMS destination to be deleted.

# Examples

## Example 1 Deleting a physical destination

The following subcommand deletes the queue named `PhysicalQueue`.

```
asadmin> delete-jmsdest --desttype queue PhysicalQueue
Command delete-jmsdest executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-jmsdest\(1\)](#), [flush-jmsdest\(1\)](#), [list-jmsdest\(1\)](#)

# delete-jms-host

Removes a JMS host

## Synopsis

```
asadmin [asadmin-options] delete-jms-host [--help]
[--target target]
jms_host_name
```

## Description

The **delete-jms-host** subcommand removes the specified Java Message Service (JMS) host.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

Deleting the default JMS host, named **default\_JMS\_host**, is not recommended.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Deletes the JMS host only from the specified target. Valid values are as follows:

##### server

Deletes the JMS host from the default server instance. This is the default value.

##### configuration-name

Deletes the JMS host from the specified configuration.

##### cluster-name

Deletes the JMS host from every server instance in the specified cluster.

##### instance-name

Deletes the JMS host from the specified server instance.

# Operands

## jms\_host\_name

The name of the host to be deleted.

# Examples

## Example 1 Deleting a JMS host

The following subcommand deletes the JMS host named `MyNewHost`.

```
asadmin> delete-jms-host MyNewHost
Command delete-jms-host executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-jms-host\(1\)](#), [jms-ping\(1\)](#), [list-jms-hosts\(1\)](#)

# delete-jms-resource

Removes a JMS resource

## Synopsis

```
asadmin [asadmin-options] delete-jms-resource [--help]
[--target target]
jndi_name
```

## Description

The `delete-jms-resource` subcommand removes the specified Java Message Service (JMS) resource. Ensure that you remove all references to this resource before executing this subcommand.

This subcommand is supported in remote mode only. Remote `asadmin` subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--target`

Deletes the JMS resource only from the specified target. Valid values are as follows:



Resources are always created for a domain as a whole but are only active for targets for which a `<resource-ref>` has been created using the `--target` option when the resource was created. This means that deleting a resource only deletes the `<resource-ref>` element for the specified `--target`, and does not delete the resource from the domain as a whole unless `domain` is specified as the `--target` for the deletion.

### server

Deletes the JMS resource from the default server instance. This is the default value.

**domain**

Deletes the JMS resource from the domain.

**cluster-name**

Deletes the JMS resource from every server instance in the specified cluster.

**instance-name**

Deletes the JMS resource from the specified server instance.

# Operands

**jndi\_name**

The JNDI name of the JMS resource to be deleted.

# Examples

## Example 1 Deleting a JMS destination resource

The following subcommand deletes the JMS destination resource named `jms/MyQueue`.

```
asadmin> delete-jms-resource jms/MyQueue
Administered object jms/MyQueue deleted.
Command delete-jms-resource executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-jms-resource\(1\)](#), [list-jms-resources\(1\)](#)

# delete-jndi-resource

Removes a JNDI resource

## Synopsis

```
asadmin [asadmin-options] delete-jndi-resource [--help]
[--target target] jndi_name
```

## Description

The **delete-jndi-resource** subcommand removes the specified JNDI resource. You must remove all associations to the JNDI resource before running this subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Valid targets are described below.

Resources are always created for a domain as a whole but are only active for targets for which a **<resource-ref>** has been created using the **--target** option when the resource was created. This means that deleting a resource only deletes the **<resource-ref>** element for the specified **--target**, and does not delete the resource from the domain as a whole unless **domain** is specified as the **--target** for the deletion.

#### server

Deletes the resource from the default server instance. This is the default value

#### domain

Deletes the resource from the domain

**cluster\_name**

Deletes the resource for every server instance in the cluster

**instance\_name**

Deletes the resource from the specified server instance

# Operands

**jndi\_name**

The name of the JNDI resource to be removed.

# Examples

## Example 1 Deleting a JNDI Resource

This example removes an existing JNDI resource named `sample_jndi_resource`.

```
asadmin> delete-jndi-resource sample_jndi_resource
Command delete-jndi-resource executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-jndi-resource\(1\)](#), [list-jndi-resources\(1\)](#)

# delete-jvm-options

Removes one or more options for the Java application launcher

## Synopsis

```
asadmin [asadmin-options] delete-jvm-options [--help]
[--target target] [--profiler={true|false}]
(jvm-option-name[=jvm-option-value]) [:jvm-option-name[=jvm-option-name]]*
```

## Description

The `delete-jvm-options` subcommand removes one or more command-line options for the Java application launcher. These options are removed from the Java configuration `java—config` element or the profiler `profiler` element of the `domain.xml` file. To see the Java application launcher options that can be deleted, use the `list-jvm-options(1)` subcommand.

The deletion of some options requires a server restart for changes to become effective. Other options are set immediately in the environment of the domain administration server (DAS) and do not require a restart.

Whether a restart is required depends on the type of option.

- Restart is not required for Java system properties whose names do not start with `-Djava.` or `-Djavax.` (including the trailing period). For example, restart is not required for the following Java system property:

`-Denvironment=Production`

- Restart is required for the following options:

- Java system properties whose names start with `-Djava.` or `-Djavax.` (including the trailing period). For example:

`-Djava.security.manager`

- Startup parameters for the Java application launcher. For example:

`-client`

`-Xmx1024m`

`-d64`

To restart the DAS, use the `restart-domain(1)` command.

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target from which you are removing Java application launcher options. Valid values are as follows:

**server**

Specifies the DAS (default).

**instance-name**

Specifies a Eclipse GlassFish instance.

**cluster-name**

Specifies a cluster.

**configuration-name**

Specifies a named configuration.

**--profiler**

Indicates whether the Java application launcher options are for the profiler. The option must have been set for a profiler for this option to be true.

# Operands

## jvm-option-name

One or more options delimited by a colon (:). The format of the operand depends on the following:

- If the option has a name and a value, the format is option-name=value.
- If the option has only a name, the format is option-name. For example, `-Xmx2048m`.



If an option name or option value contains a colon, the backslash (\) must be used to escape the colon in the name or value. Other characters might also require an escape character. For more information about escape characters in subcommand options, see the [asadmin\(1M\)](#) man page.

# Examples

## Example 1 Deleting Java Application Launcher Options

This example removes multiple Java application launcher options.

```
asadmin> delete-jvm-options -Doption1=value1  
"-Doption1=value1:-Doption2=value2"  
Command delete-jvm-options executed successfully
```

## Example 2 Deleting a Java Application Launcher Option From the Profiler

This example removes a Java application launcher startup parameter for the profiler.

```
asadmin> delete-jvm-options --profiler=true -XX:MaxPermSize=192m  
Command delete-jvm-options executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jvm-options\(1\)](#), [list-jvm-options\(1\)](#), [restart-domain\(1\)](#)

For more information about the Java application launcher, see the reference page for the operating system that you are using:

- Oracle Solaris and Linux: java - the Java application launcher (<http://java.sun.com/javase/7/docs/technotes/tools/solaris/java.html>)
- Windows: java - the Java application launcher (<http://java.sun.com/javase/7/docs/technotes/tools/windows/java.html>)



# delete-lifecycle-module

Removes the lifecycle module

## Synopsis

```
asadmin [asadmin-options] delete-lifecycle-module [--help]
[--target target] module_name
```

## Description

The **delete-lifecycle-module** subcommand removes a lifecycle module. A lifecycle module provides a means of running a short or long duration Java-based task at a specific stage in the server life cycle. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Indicates the location where the lifecycle module is to be deleted. Valid values are

- **server**- Specifies the default server instance as the target for deleting the lifecycle module. **server** is the name of the default server instance and is the default value for this option.
- **cluster\_name**- Specifies a particular cluster as the target for deleting the lifecycle module.
- **instance\_name**- Specifies a particular server instance as the target for deleting the lifecycle module.

## Operands

### module\_name

This operand is a unique identifier for the deployed server lifecycle event listener module.

# Examples

## Example 1 Deleting a Lifecycle Module

The following example deletes a lifecycle module named `customSetup`.

```
asadmin> delete-lifecycle-module customSetup  
Command delete-lifecycle-module executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-lifecycle-module\(1\)](#), [list-lifecycle-modules\(1\)](#)

# delete-local-instance

Deletes a Eclipse GlassFish instance on the machine where the subcommand is run

## Synopsis

```
asadmin [asadmin-options] delete-local-instance [--help]
[--nodedir node-dir] [--node node-name]
[instance-name]
```

## Description

The **delete-local-instance** subcommand deletes a Eclipse GlassFish instance on the machine where the subcommand is run. This subcommand does not require the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured. You must run this command from the machine where the instance resides.

The subcommand can delete any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can delete an instance that was created by using the [create-instance\(1\)](#) subcommand.

The instance that is being deleted must not be running. Otherwise, an error occurs.

The subcommand deletes an instance by performing the following actions:

- Removing the instance from the configuration of the domain administration server (DAS)
- Deleting the instance's files from file system

If the instance that is being deleted is the only instance that is using the node directory, that directory is also removed.

If a standalone instance is deleted, the instance's standalone configuration is also deleted. A standalone instance refers to a configuration that is named instance-name`-config` to which no other clusters or unclustered instances refer.

The **delete-local-instance** subcommand does not contact the DAS to determine the node on which the instance resides. To determine the node on which the instance resides, the subcommand searches the directory that contains the node directories. If multiple node directories exist, the node must be specified as an option of the subcommand.

If no operand is specified and only one instance resides on the specified node, the subcommand deletes the instance. If no operand is specified and multiple instances reside on the node, an error occurs.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--nodedir`

Specifies the directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is `as-install/nodes`.

`--node`

Specifies the node on which the instance resides. This option may be omitted only if the directory that the `--nodedir` option specifies contains only one node directory. Otherwise, this option is required.

## Operands

### instance-name

The name of the instance to delete. This operand may be omitted if only one instance resides on the specified node. Otherwise, this operand is required.

## Examples

### Example 1 Deleting an Instance

This example deletes the instance `pmdsainst`.

```
asadmin> delete-local-instance pmdsainst
Command delete-local-instance executed successfully.
```

## Exit Status

`0`

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [start-instance\(1\)](#), [start-local-instance\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#)

# delete-managed-executor-service

Removes a managed executor service resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] delete-managed-executor-service [--help]
[--target target]
managed_executor_service_name
```

## Description

The **delete-managed-executor-service** subcommand removes a managed executor service resource with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target from which you are deleting the resource. Valid targets are:

##### server

Deletes the resource from the default server instance. This is the default value.

##### domain

Deletes the resource from the domain.

##### cluster\_name

Deletes the resource from every server instance in the specified cluster.

##### instance\_name

Deletes the resource from the specified server instance.

# Operands

## managed\_executor\_service\_name

The JNDI name of the resource to be deleted.

## Examples

### Example 1 Deleting a Managed Executor Service Resource

This example deletes the managed executor service resource named `concurrent/myExecutor`.

```
asadmin> delete-managed-executor-service concurrent/myExecutor
Managed executor service concurrent/myExecutor deleted successfully.
Command delete-managed-executor-service executed successfully.
```

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-managed-executor-service\(1\)](#), [list-managed-executor-services\(1\)](#)

# delete-managed-scheduled-executor-service

Removes a managed scheduled executor service resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] delete-managed-scheduled-executor-service [--help]
[--target target]
managed_scheduled_executor_service_name
```

## Description

The `delete-managed-scheduled-executor-service` subcommand removes a managed scheduled executor service resource with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target from which you are deleting the resource. Valid targets are:

##### server

Deletes the resource from the default server instance. This is the default value.

##### domain

Deletes the resource from the domain.

##### cluster\_name

Deletes the resource from every server instance in the specified cluster.

##### instance\_name

Deletes the resource from the specified server instance.

# Operands

## managed\_scheduled\_executor\_service\_name

The JNDI name of the resource to be deleted.

# Examples

## Example 1 Deleting a Managed Scheduled Executor Service Resource

This example deletes the managed scheduled executor service resource named `concurrent/myScheduledExecutor`.

```
asadmin> delete-managed-scheduled-executor-service concurrent/myScheduledExecutor
Managed scheduled executor service concurrent/myScheduledExecutor deleted successfully.
Command delete-managed-scheduled-executor-service executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-managed-scheduled-executor-service\(1\)](#), [list-managed-scheduled-executor-services\(1\)](#)

# delete-managed-thread-factory

Removes a managed thread factory resource with the specified JNDI name

## Synopsis

```
asadmin [asadmin-options] delete-managed-thread-factory [--help]
[--target target]
managed_thread_factory_name
```

## Description

The **delete-managed-thread-factory** subcommand removes a managed thread factory resource with the specified JNDI name.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target from which you are deleting the resource. Valid targets are:

##### server

Deletes the resource from the default server instance. This is the default value.

##### domain

Deletes the resource from the domain.

##### cluster\_name

Deletes the resource from every server instance in the specified cluster.

##### instance\_name

Deletes the resource from the specified server instance.

# Operands

## managed\_thread\_factory\_name

The JNDI name of the resource to be deleted.

## Examples

### Example 1 Deleting a Managed Thread Factory Resource

This example deletes the managed thread factory resource named `concurrent/myThreadFactory`.

```
asadmin> delete-managed-thread-factory concurrent/myThreadFactory
Managed thread factory concurrent/myThreadFactory deleted successfully.
Command delete-managed-thread-factory executed successfully.
```

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-managed-thread-factory\(1\)](#), [list-managed-thread-factories\(1\)](#)

# delete-message-security-provider

Enables administrators to delete a message security provider

## Synopsis

```
asadmin [asadmin-options] delete-message-security-provider [--help]
[--target target]
--layer message_layer
provider_name
```

## Description

The `delete-message-security-provider` subcommand enables administrators to delete a message security provider.

In terms of what happens when this subcommand is run, the `provider-config` sub-element for the given message layer (`message-security-config` element of `domain.xml`) is deleted. The `domain.xml` file specifies parameters and properties to the Eclipse GlassFish. The options specified in the list below apply to attributes within the `message-security-config` and `provider-config` sub-elements of the `domain.xml` file.

If the message-layer (`message-security-config` attribute) does not exist, it is created, and then the `provider-config` is created under it.

This command is supported in remote mode only.

## Options

If an option has a short option name, then the short option precedes the long option name. Short options have one dash whereas long options have two dashes.

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target from which you are deleting the message security provider. Valid values are

**server**

Deletes the message security provider from the default server instance **server** and is the default value

**domain**

Deletes the message security provider from the domain.

**cluster\_name**

Deletes the message security provider from every server instance in the cluster.

**instance\_name**

Deletes the message security provider from a particular sever instance.

**--layer**

The message-layer from which the provider has to be deleted. The default value is **HttpServlet**.

## Operands

**provider\_name**

The name of the provider used to reference the **provider-config** element.

## Examples

### Example 1 Deleting a message security provider

The following example shows how to delete a message security provider for a client.

```
asadmin> delete-message-security-provider  
--layer SOAP mySecurityProvider
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[create-message-security-provider\(1\)](#), [list-message-security-providers\(1\)](#)

# delete-module-config

Removes the configuration of a module from `domain.xml`

## Synopsis

```
asadmin [asadmin-options] delete-module-config [--help]
[--target target]
service_name
```

## Description

The `delete-module-config` subcommand removes the configuration of a module from `domain.xml` and causes the module to use the default configuration included in the module.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target from which the configuration is to be deleted. Possible values are as follows:

##### server

Deletes the configuration from the default server instance. This is the default value.

##### domain

Deletes the configuration from the default domain.

##### cluster-name

Deletes the configuration from every server instance in the specified cluster.

##### instance-name

Deletes the configuration from the specified instance.

# Operands

## service\_name

The name of the module for which configuration is to be removed.

## Examples

### Example 1 Deleting a Default Configuration From domain.xml

This example deletes the configuration of the web container module from `domain1` in `server-config` (the default configuration).

```
asadmin> delete-module-config web-container
Command delete-module-config executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-module-config\(1\)](#), [get-active-module-config\(1\)](#)

# delete-network-listener

Removes a network listener

## Synopsis

```
asadmin [asadmin-options] delete-network-listener [--help]
[--target target]
listener-name
```

## Description

The **delete-network-listener** subcommand removes the specified network listener. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Deletes the network listener only from the specified target. Valid values are as follows:

##### server

Deletes the network listener from the default server instance. This is the default value.

##### configuration-name

Deletes the network listener from the specified configuration.

##### cluster-name

Deletes the network listener from all server instances in the specified cluster.

##### standalone-instance-name

Deletes the network listener from the specified standalone server instance.

# Operands

## listener-name

The name of the network listener to be deleted.

## Examples

### Example 1 Deleting a Network Listener

The following command deletes the network listener named `sampleListener`:

```
asadmin> delete-network-listener sampleListener
Command delete-network-listener executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-network-listener\(1\)](#), [list-network-listeners\(1\)](#)

# delete-node-config

Deletes a node that is not enabled for remote communication

## Synopsis

```
asadmin [asadmin-options] delete-node-config [--help]  
node-name
```

## Description

The [delete-node-config](#) subcommand deletes a node that is not enabled for remote communication from the domain. This subcommand does not require the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured.

This subcommand can delete only a node that is not enabled for remote communication. The subcommand for deleting other types of nodes depends on the type of the node:

- A node that is enabled for remote communication over DCOM must be deleted by using the [delete-node-dcom\(1\)](#) subcommand.
- A node that is enabled for remote communication over SSH must be deleted by using the [delete-node-ssh\(1\)](#) subcommand.

To determine whether a node is enabled for remote communication, use the [list-nodes\(1\)](#) subcommand.

No Eclipse GlassFish instances must reside on the node that is being deleted. Otherwise, the subcommand fails. Before running this subcommand, delete any instances that reside on the node by using, for example, the [delete-instance\(1\)](#) subcommand or the [delete-local-instance\(1\)](#) subcommand.



The predefined node `localhost`-domain cannot be deleted.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

[--help](#)

[-?](#)

Displays the help text for the subcommand.

# Operands

## node-name

The name of the node to delete. The node must not be enabled for communication over DCOM or SSH. Otherwise, an error occurs.

## Examples

### Example 1 Deleting a Node That Is Not Enabled for Remote Communication

This example deletes the node `sj03`, which is not enabled for remote communication.

```
asadmin> delete-node-config sj03  
Command delete-node-config executed successfully.
```

## Exit Status

`0`

command executed successfully

`1`

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [delete-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-nodes\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-config\(1\)](#), [update-node-dcom\(1\)](#), [update-node-ssh\(1\)](#)

# delete-node-dcom

Deletes a node that is enabled for communication over DCOM

## Synopsis

```
asadmin [asadmin-options] delete-node-dcom [--help]
[--uninstall={false|true}] [--force={false|true}]
node-name
```

## Description

The [delete-node-dcom](#) subcommand deletes a node that is enabled for communication over the Distributed Component Object Model (DCOM) remote protocol from the domain. The DCOM protocol is available only on Windows systems. This subcommand does not require DCOM to be configured.

This subcommand can delete only a node that is enabled for communication over DCOM. The subcommand for deleting other types of nodes depends on the type of the node:

- A node that is enabled for communication over secure shell (SSH) must be deleted by using the [delete-node-ssh\(1\)](#) subcommand.
- A node that is not enabled for communication must be deleted by using the [delete-node-config\(1\)](#) subcommand.

To determine whether a node is enabled for communication over DCOM, use the [list-nodes\(1\)](#) subcommand.

No Eclipse GlassFish instances must reside on the node that is being deleted. Otherwise, the subcommand fails. Before running this subcommand, delete any instances that reside on the node by using, for example, the [delete-instance\(1\)](#) subcommand or the [delete-local-instance\(1\)](#) subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## --uninstall

Specifies whether the Eclipse GlassFish software is uninstalled from host that the node represents. Possible values are as follows:

### false

The Eclipse GlassFish software is not uninstalled from the host (default).

### true

The Eclipse GlassFish software is uninstalled from the host. By default, if any node except the predefined node `localhost`-domain resides on any host from which Eclipse GlassFish software is being uninstalled, the subcommand fails.

To uninstall the Eclipse GlassFish software from a host on which user-defined nodes reside, set the `--force` option to `true`.

If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

## --force

If `--uninstall` is true, specifies whether the subcommand uninstalls the Eclipse GlassFish software from a host even if a user-defined node resides on the host. Possible values are as follows:

### false

If a user-defined node resides on a host, the software is not uninstalled and the subcommand fails (default).

If the `--force` option is `false`, the subcommand removes only the Eclipse GlassFish software files. Other content if the parent of the base installation directory, such as configuration files, are not removed.

### true

The subcommand uninstalls the Eclipse GlassFish software from the host even if a user-defined node resides on the host.

If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

# Operands

## node-name

The name of the node to delete. The node must enabled for communication over DCOM. Otherwise, an error occurs.

# Examples

## Example 1 Deleting a Node That Is Enabled for Communication Over DCOM

This example deletes the node `xkyd`, which is enabled for communication over DCOM.

```
asadmin> delete-node-dcom xkyd
Command delete-node-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-dcom\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [delete-node-config\(1\)](#), [delete-node-ssh\(1\)](#), [install-node-dcom\(1\)](#), [list-nodes\(1\)](#), [uninstall-node-dcom\(1\)](#), [update-node-dcom\(1\)](#)

# delete-node-ssh

Deletes a node that is enabled for communication over SSH

## Synopsis

```
asadmin [asadmin-options] delete-node-ssh [--help]
[--uninstall={false|true}] [--force={false|true}]
node-name
```

## Description

The [delete-node-ssh](#) subcommand deletes a node that is enabled for communication over secure shell (SSH) from the domain. This subcommand does not require SSH to be configured.

This subcommand can delete only a node that is enabled for communication over SSH. The subcommand for deleting other types of nodes depends on the type of the node:

- A node that is enabled for communication over the Distributed Component Object Model (DCOM) remote protocol must be deleted by using the [delete-node-dcom\(1\)](#) subcommand.
- A node that is not enabled for remote communication must be deleted by using the [delete-node-config\(1\)](#) subcommand.

To determine whether a node is enabled for communication over SSH, use the [list-nodes\(1\)](#) subcommand.

No Eclipse GlassFish instances must reside on the node that is being deleted. Otherwise, the subcommand fails. Before running this subcommand, delete any instances that reside on the node by using, for example, the [delete-instance\(1\)](#) subcommand or the [delete-local-instance\(1\)](#) subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--uninstall**

Specifies whether the Eclipse GlassFish software is uninstalled from host that the node represents. Possible values are as follows:

**false**

The Eclipse GlassFish software is not uninstalled from the host (default).

**true**

The Eclipse GlassFish software is uninstalled from the host. By default, if any node except the predefined node `localhost`-domain resides on any host from which Eclipse GlassFish software is being uninstalled, the subcommand fails. To uninstall the Eclipse GlassFish software from a host on which user-defined nodes reside, set the `--force` option to `true`. If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

**--force**

If `--uninstall` is true, specifies whether the subcommand uninstalls the Eclipse GlassFish software from a host even if a user-defined node resides on the host. Possible values are as follows:

**false**

If a user-defined node resides on a host, the software is not uninstalled and the subcommand fails (default).

If the `--force` option is `false`, the subcommand removes only the Eclipse GlassFish software files. Other content if the parent of the base installation directory, such as configuration files, are not removed.

**true**

The subcommand uninstalls the Eclipse GlassFish software from the host even if a user-defined node resides on the host.

If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

## Operands

**node-name**

The name of the node to delete. The node must enabled for communication over SSH. Otherwise, an error occurs.

## Examples

## Example 1 Deleting a Node That Is Enabled for Communication Over SSH

This example deletes the node `eg1`, which is enabled for communication over SSH.

```
asadmin> delete-node-ssh eg1
Command delete-node-ssh executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-nodes\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-dcom\(1\)](#), [update-node-ssh\(1\)](#)

# delete-password-alias

Deletes a password alias

## Synopsis

```
asadmin [asadmin-options] delete-password-alias [--help]  
aliasname
```

## Description

This subcommand deletes a password alias.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### aliasname

This is the name of the substitute password as it appears in [domain.xml](#).

## Examples

### Example 1 Deleting a Password Alias

```
asadmin>delete-password-alias  
jmspassword-alias
```

Command delete-password-alias executed successfully

---

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-password-alias\(1\)](#), [list-password-aliases\(1\)](#), [update-password-alias\(1\)](#)

# delete-profiler

Removes the profiler element

## Synopsis

```
asadmin [asadmin-options] delete-profiler [--help]
[--target target_name]
```

## Description

The **delete-profiler** subcommand deletes the profiler element in the Java configuration. Only one profiler can exist at a time. If you attempt to create a profiler while one already exists, an error message is displayed and the existing profiler must be deleted.

For changes to take effect, the server must restarted.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target profiler element which you are deleting. Valid values are

##### server

Deletes the profiler element for the default server instance **server** and is the default value.

##### configuration\_name

Deletes the profiler element for the named configuration.

##### cluster\_name

Deletes the profiler element for every server instance in the cluster.

##### instance\_name

Deletes the profiler element for a particular server instance.

# Examples

## Example 1 Deleting a Profile

This example deletes the profiler named `sample_profiler`.

```
asadmin> delete-profiler sample_profiler
Command delete-profiler executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-profiler\(1\)](#)

# delete-protocol

Removes a protocol

## Synopsis

```
asadmin [asadmin-options] delete-protocol [--help]
[--target target]
protocol-name
```

## Description

The **delete-protocol** subcommand removes the specified protocol. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Deletes the protocol only from the specified target. Valid values are as follows:

**server**

Deletes the protocol from the default server instance. This is the default value.

**configuration-name**

Deletes the protocol from the specified configuration.

**cluster-name**

Deletes the protocol from all server instances in the specified cluster.

**standalone-instance-name**

Deletes the protocol from the specified standalone server instance.

# Operands

## protocol-name

The name of the protocol to be deleted.

## Examples

### Example 1 Deleting a Protocol

The following command deletes the protocol named **http-1**:

```
asadmin> delete-protocol http-1
Command delete-protocol executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-protocol\(1\)](#), [list-protocols\(1\)](#)

# delete-protocol-filter

Removes a protocol filter

## Synopsis

```
asadmin [asadmin-options] delete-protocol-filter [--help]
--protocol protocol-name
[--target server]
protocol-filter-name
```

## Description

The `delete-protocol-filter` subcommand removes the specified protocol filter. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --protocol-name

The name of the associated protocol.

#### --target

Deletes the protocol filter only from the specified target. Valid values are as follows:

##### server

Deletes the protocol filter from the default server instance. This is the default value.

##### configuration-name

Deletes the protocol filter from the specified configuration.

##### cluster-name

Deletes the protocol filter from all server instances in the specified cluster.

##### standalone-instance-name

Deletes the protocol filter from the specified standalone server instance.

# Operands

## protocol-filter-name

The name of the protocol filter to be deleted.

# Examples

## Example 1 Deleting a Protocol Filter

The following command deletes the protocol filter named `http1-filter`:

```
asadmin> delete-protocol-filter --protocol http1 http1-filter
Command delete-protocol-filter executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[create-protocol-filter\(1\)](#), [list-protocol-filters\(1\)](#)

# delete-protocol-finder

Removes a protocol finder

## Synopsis

```
asadmin [asadmin-options] delete-protocol-finder [--help]
--protocol protocol-name
[--target server]
protocol-finder-name
```

## Description

The `delete-protocol-finder` subcommand removes the specified protocol finder. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --protocol-name

The name of the associated protocol.

#### --target

Deletes the protocol finder only from the specified target. Valid values are as follows:

##### server

Deletes the protocol finder from the default server instance. This is the default value.

##### configuration-name

Deletes the protocol finder from the specified configuration.

##### cluster-name

Deletes the protocol finder from all server instances in the specified cluster.

##### standalone-instance-name

Deletes the protocol finder from the specified standalone server instance.

# Operands

## protocol-finder-name

The name of the protocol finder to be deleted.

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-protocol-finder\(1\)](#), [list-protocol-finders\(1\)](#)

# delete-resource-adapter-config

Deletes the resource adapter configuration

## Synopsis

```
asadmin [asadmin-options] delete-resource-adapter-config [--help]
raname
```

## Description

The **delete-resource-adapter-config** subcommand deletes the configuration information for the connector module.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option is deprecated.

## Operands

### raname

Specifies the connector module name.

## Examples

### Example 1 Deleting a Resource Adapter Configuration

This example deletes the configuration information for **ra1**.

```
asadmin> delete-resource-adapter-config ra1
Command delete-resource-adapter-config executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-resource-adapter-config\(1\)](#), [list-resource-adapter-configs\(1\)](#)

# delete-resource-ref

Removes a reference to a resource

## Synopsis

```
asadmin [asadmin-options] delete-resource-ref [--help]
[--target target] reference_name
```

## Description

The **delete-resource-ref** subcommand removes from a cluster or an unclustered server instance a reference to a resource (for example, a JDBC resource). This effectively results in the removal of the resource from the JNDI tree of the targeted instance or cluster.

The target instance or instances making up the cluster need not be running or available for this subcommand to succeed. If one or more instances are not available, they will no longer load the resource in the JNDI tree the next time they start.

Removal of the reference does not result in removal of the resource from the domain. The resource is removed only by the **delete** subcommand for that resource (for example, **delete-jdbc-resource**).

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target from which you are removing the resource reference. Valid values are

**server**

Removes the resource reference from the default server instance **server** and is the default value.

**cluster\_name**

Removes the resource reference from every server instance in the cluster.

**instance\_name**

Removes the resource reference from the named unclustered server instance.

## Operands

**reference\_name**

The name or JNDI name of the resource.

## Examples

### Example 1 Removing a Reference to a Resource

This example removes a reference to the JMS destination resource `jms/Topic` on the cluster `cluster1`.

```
asadmin> delete-resource-ref --target cluster1 jms/Topic  
resource-ref jms/Topic deleted successfully.  
Command delete-resource-ref executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-resource-ref\(1\)](#), [list-resource-references\(1\)](#)

# delete-ssl

Deletes the SSL element in the selected HTTP listener, IIOP listener, or IIOP service

## Synopsis

```
asadmin [asadmin-options] delete-ssl [--help]
[--target target]
--type listener_or_service_type
listener_id
```

## Description

The **delete-ssl** subcommand deletes the SSL element in the selected HTTP listener, IIOP listener, or IIOP service.

The `listener_id` is not required if the `--type` is **iop-service**.

This subcommand is supported in remote mode only.

## Options

If an option has a short option name, then the short option precedes the long option name. Short options have one dash whereas long options have two dashes.

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

`-?`

Displays the help text for the subcommand.

#### --target

Specifies the target on which you are configuring the ssl element. The following values are valid:

#### server

Specifies the server in which the iiop-service or HTTP/IIOP listener is to be unconfigured for SSL.

#### config

Specifies the configuration that contains the HTTP/IIOP listener or iiop-service for which SSL is to be unconfigured.

**cluster**

Specifies the cluster in which the HTTP/IOP listener or iiop-service is to be unconfigured for SSL. All the server instances in the cluster will get SSL unconfigured for the respective listener or iiop-service.

**instance**

Specifies the instance in which the HTTP/IOP listener or iiop-service is to be unconfigured for SSL.

**--type**

The type of service or listener for which the SSL is deleted. The type must be one of the following types:

- **http-listener**
- **iiop-listener**
- **iiop-service**

## Operands

**listener\_id**

The ID of the listener from which the SSL element is to be deleted.

The `listener_id` operand is not required if the `--type` is **iiop-service**.

## Examples

### Example 1 Deleting an SSL element from an HTTP listener

The following example shows how to delete an SSL element from an HTTP listener named **http-listener-1**.

```
asadmin> delete-ssl
--type http-listener http-listener-1
Command delete-ssl executed successfully.
```

## Exit Status

**0**

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-ssl\(1\)](#)

# delete-system-property

Removes a system property of the domain, configuration, cluster, or server instance, one at a time

## Synopsis

```
asadmin [asadmin-options] delete-system-property [--help]
[--target target_name ]
[property_name]
```

## Description

The **delete-system-property** subcommand deletes a system property of a domain, configuration, cluster, or server instance. Make sure that the system property is not referenced elsewhere in the configuration before deleting it.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This option specifies the target on which you are deleting the system properties. The valid targets for this subcommand are instance, cluster, configuration, domain, and server. Server is the default option.

## Operands

### property\_name

The name of the system property to remove.

## Examples

## Example 1 Deleting a System Property

This example deletes the system property named `http-listener-port`.

```
asadmin> delete-system-property http-listener-port  
Command delete-system-property executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-system-properties\(1\)](#), [list-system-properties\(1\)](#)

# delete-threadpool

Removes a thread pool

## Synopsis

```
asadmin [asadmin-options] delete-threadpool [--help]
[--target target] threadpool-id
```

## Description

Removes the thread pool with the specified ID. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target from which you are removing the thread pool. Valid values are as follows:

##### server

Deletes the thread pool for the default Eclipse GlassFish instance `server` and is the default value.

##### configuration-name

Deletes the thread pool for the named configuration.

##### cluster-name

Deletes the thread pool for every instance in the cluster.

##### instance-name

Deletes the thread pool for a particular instance.

## Operands

## threadpool-id

An ID for the work queue, for example, `thread-pool1`, `threadpool-2`, and so forth.

# Examples

### Example 1 Deleting a Thread Pool

This example deletes `threadpool-1`.

```
asadmin> delete-threadpool threadpool-1
Command delete-threadpool executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-threadpool\(1\)](#), [list-threadpools\(1\)](#)

# delete-transport

Removes a transport

## Synopsis

```
asadmin [asadmin-options] delete-transport [--help]
[--target target]
transport-name
```

## Description

The **delete-transport** subcommand removes the specified transport. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Deletes the transport only from the specified target. Valid values are as follows:

**server**

Deletes the transport from the default server instance. This is the default value.

**configuration-name**

Deletes the transport from the specified configuration.

**cluster-name**

Deletes the transport from all server instances in the specified cluster.

**standalone-instance-name**

Deletes the transport from the specified standalone server instance.

# Operands

## transport-name

The name of the transport to be deleted.

## Examples

### Example 1 Deleting a Transport

The following command deletes the transport named `http1-trans`:

```
asadmin> delete-transport http1-trans
Command delete-transport executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-transport\(1\)](#), [list-transports\(1\)](#)

# delete-virtual-server

Removes a virtual server

## Synopsis

```
asadmin [asadmin-options] delete-virtual-server [--help]
[--target target] virtual-server-id
```

## Description

The **delete-virtual-server** subcommand removes the virtual server with the specified virtual server ID. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Deletes the virtual server only from the specified target. Valid values are as follows:

##### server

Deletes the virtual server from the default server instance. This is the default value.

##### configuration-name

Deletes the virtual server from the specified configuration.

##### cluster-name

Deletes the virtual server from all server instances in the specified cluster.

##### standalone-instance-name

Deletes the virtual server from the specified standalone server instance.

## Operands

## virtual-server-id

The unique identifier for the virtual server to be deleted.

# Examples

## Example 1 Deleting a Virtual Server

The following command deletes the virtual server named `sample_vs1`:

```
asadmin> delete-virtual-server sample_vs1
Command delete-virtual-server executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-virtual-server\(1\)](#), [list-virtual-servers\(1\)](#)

# deploy

Deploys the specified component

## Synopsis

```
asadmin [asadmin-options] deploy [--help]
[--force={false|true}]
[--virtualservers virtual_servers]
[--contextroot context_root]
[--precompilejsp={false|true}]
[--verify={false|true}]
[--name component_name]
[--upload={true|false}]
[--retrieve local_dirpath]
[--dbvendorname dbvendorname]
[--createtables={true|false}|--dropandcreatetables={true|false}]
[--uniquetablenames={true|false}]
[--deploymentplan deployment_plan]
[--altdd alternate_deploymentdescriptor]
[--runtimealtdd runtime_alternate_deploymentdescriptor]
[--deploymentorder deployment_order]
[--enabled={true|false}]
[--generateremistubs={false|true}]
[--availabilityenabled={false|true}]
[--asyncreplication={true|false}]
[--lbenabled={true|false}]
[--keepstate={false|true}]
[--libraries jar_file[,jar_file]*]
[--target target]
[--type pkg-type]
[--properties(name=value)[:name=value]*]
[file_archive|filepath]
```

## Description

The `deploy` subcommand deploys applications to the server. Applications can be enterprise applications, web applications, Enterprise JavaBeans (EJB) modules, connector modules, and application client modules. If the component is already deployed or already exists, it is forcibly redeployed if the `--force` option is set to `true` (default is `false`).

The `--createtables` and `--dropandcreatetables` options are boolean flags and therefore can take the values of true or false. These options are only used during deployment of CMP beans that have not been mapped to a database (that is, no `sun-cmp-mappings.xml` descriptor is provided in the module's

---

**META-INF** directory). They are ignored otherwise.

The **--createtables** and **--dropandcreatetables** options are mutually exclusive; only one should be used. If drop and/or create tables fails, the deployment does not fail; a warning message is provided in the log file.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --force

If set to **true**, redeloys the component even if the specified component has already been deployed or already exists. Default is **false**.

#### --virtualservers

One or more virtual server IDs. Multiple IDs are separated by commas.

#### --contextroot

Valid only if the archive is a web module. It is ignored for other archive types; it will be the value specified by default-context-path in web.xml, if specified; defaults to filename without extension.

#### --precompilejsp

By default this option does not allow the JSP to be precompiled during deployment. Instead, JSPs are compiled during runtime. Default is **false**.

#### --verify

If set to true and the required verifier packages are installed from the Update Tool, the syntax and semantics of the deployment descriptor is verified. Default is **false**.

#### --name

Name of the deployable component.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see "Module and Application Versions" in Eclipse GlassFish Application Deployment Guide.

**--upload**

Specifies whether the subcommand uploads the file to the DAS. In most situations, this option can be omitted.

Valid values are as follows:

**false**

The subcommand does not upload the file and attempts to access the file through the specified file name. If the DAS cannot access the file, the subcommand fails.

For example, the DAS might be running as a different user than the administration user and does not have read access to the file. In this situation, the subcommand fails if the **--upload** option is **false**.

**true**

The subcommand uploads the file to the DAS over the network connection.

The default value depends on whether the DAS is on the host where the subcommand is run or is on a remote host.

- If the DAS is on the host where the subcommand is run, the default is **false**.
- If the DAS is on a remote host, the default is **true**.

If a directory filepath is specified, this option is ignored.

**--retrieve**

Retrieves the client stub JAR file from the server machine to the local directory.

**--dbvendorname**

Specifies the name of the database vendor for which tables are created. Supported values include **db2**, **mssql**, **mysql**, **oracle**, **derby**, **javadb**, **postgresql**, and **sybase**. These values are case-insensitive. If not specified, the value of the **database-vendor-name** attribute in **glassfish-ejb-jar.xml** is used. If no value is specified, a connection is made to the resource specified by the **jndi-name** subelement of the **cmp-resource** element in the **glassfish-ejb-jar.xml** file, and the database vendor name is read. If the connection cannot be established, or if the value is not recognized, SQL-92 compliance is presumed.

**--createtables**

If specified as true, creates tables at deployment of an application with unmapped CMP beans. If specified as false, tables are not created. If not specified, the value of the **create-tables-at-deploy** entry in the **cmp-resource** element of the **glassfish-ejb-jar.xml** file determines whether or not tables are created. No unique constraints are created for the tables.

**--dropandcreatetables**

If specified as true when the component is redeployed, the tables created by the previous deployment are dropped before creating the new tables. Applies to deployed applications with unmapped CMP beans. Preexisting tables will not be dropped on the initial deployment of an application or on a deployment that follows an explicit undeploy. If specified as false, tables are

neither dropped nor created. If not specified, the tables are dropped if the `drop-tables-at-undeploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file is set to true, and the new tables are created if the `create-tables-at-deploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file is set to true.

#### --uniquetablenames

Guarantees unique table names for all the beans and results in a hash code added to the table names. This is useful if you have an application with case-sensitive bean names. Applies to applications with unmapped CMP beans.

#### --deploymentplan

Deploys the deployment plan, which is a JAR file that contains Eclipse GlassFish descriptors. Specify this option when deploying a pure EAR file. A pure EAR file is an EAR without Eclipse GlassFish descriptors.

#### --altdd

Deploys the application using a Jakarta EE standard deployment descriptor that resides outside of the application archive. Specify an absolute path or a relative path to the alternate deployment descriptor file. The alternate deployment descriptor overrides the top-level deployment descriptor packaged in the archive. For example, for an EAR, the `--altdd` option overrides `application.xml`. For a standalone module, the `--altdd` option overrides the top-level module descriptor such as `web.xml`.

#### --runtimealtdd

Deploys the application using a Eclipse GlassFish runtime deployment descriptor that resides outside of the application archive. Specify an absolute path or a relative path to the alternate deployment descriptor file. The alternate deployment descriptor overrides the top-level deployment descriptor packaged in the archive. For example, for an EAR, the `--runtimealtdd` option overrides `glassfish-application.xml`. For a standalone module, the `--runtimealtdd` option overrides the top-level module descriptor such as `glassfish-web.xml`. Applies to Eclipse GlassFish deployment descriptors only (`glassfish-*.xml`); the name of the alternate deployment descriptor file must begin with `glassfish-`. Does not apply to `sun-*.xml` deployment descriptors, which are deprecated.

#### --deploymentorder

Specifies the deployment order of the application. This is useful if the application has dependencies and must be loaded in a certain order at server startup. The deployment order is specified as an integer. The default value is 100. Applications with lower numbers are loaded before applications with higher numbers. For example, an application with a deployment order of 102 is loaded before an application with a deployment order of 110. If a deployment order is not specified, the default value of 100 is assigned. If two applications have the same deployment order, the first application to be deployed is the first application to be loaded at server startup.

The deployment order is typically specified when the application is first deployed but can also be specified or changed after initial deployment using the `set` subcommand. You can view the deployment order of an application using the `get` subcommand.

**--enabled**

Allows users to access the application. If set to `false`, users will not be able to access the application. This option enables the application on the specified target instance or cluster. If you deploy to the target `domain`, this option is ignored, since deploying to the domain doesn't deploy to a specific instance or cluster. The default is `true`.

**--generatermistubs**

If set to `true`, static RMI-IIOP stubs are generated and put into the `client.jar`. If set to `false`, the stubs are not generated. Default is `false`.

**--availabilityenabled**

This option controls whether high-availability is enabled for web sessions and for stateful session bean (SFSB) checkpointing and potentially passivation. If set to false (default) all web session saving and SFSB checkpointing is disabled for the specified application, web application, or EJB module. If set to true, the specified application or module is enabled for high-availability. Set this option to true only if high availability is configured and enabled at higher levels, such as the server and container levels.

**--asyncreplication**

This option controls whether web session and SFSB states for which high availability is enabled are first buffered and then replicated using a separate asynchronous thread. If set to true (default), performance is improved but availability is reduced. If the instance where states are buffered but not yet replicated fails, the states are lost. If set to false, performance is reduced but availability is guaranteed. States are not buffered but immediately transmitted to other instances in the cluster.

**--lbenabled**

This option controls whether the deployed application is available for load balancing. The default is true.

**--keepstate**

This option controls whether web sessions, SFSB instances, and persistently created EJB timers are retained between redeployments.

The default is false. This option is supported only on the default server instance, named `server`. It is not supported and ignored for any other target.

Some changes to an application between redeployments prevent this feature from working properly. For example, do not change the set of instance variables in the SFSB bean class.

For web applications, this feature is applicable only if in the `glassfish-web-app.xml` file the `persistence-type` attribute of the `session-manager` element is `file`.

For stateful session bean instances, the persistence type without high availability is set in the server (the `sfsb-persistence-type` attribute) and must be set to `file`, which is the default and recommended value.

If any active web session, SFSB instance, or EJB timer fails to be preserved or restored, none of these will be available when the redeployment is complete. However, the redeployment continues and a warning is logged.

To preserve active state data, Eclipse GlassFish serializes the data and saves it in memory. To restore the data, the class loader of the newly redeployed application deserializes the data that was previously saved.

#### --libraries

A comma-separated list of library JAR files. Specify the library JAR files by their relative or absolute paths. Specify relative paths relative to domain-dir ` /lib/applibs ` . The libraries are made available to the application in the order specified.

#### --target

Specifies the target to which you are deploying. Valid values are:

##### server

Deploys the component to the default server instance `server` and is the default value.

##### domain

Deploys the component to the domain. If `domain` is the target for an initial deployment, the application is deployed to the domain, but no server instances or clusters reference the application. If `domain` is the target for a redeployment (the `--force` option is set to true), and dynamic reconfiguration is enabled for the clusters or server instances that reference the application, the referencing clusters or server instances automatically get the new version of the application. If redeploying, and dynamic configuration is disabled, the referencing clusters or server instances do not get the new version of the application until the clustered or standalone server instances are restarted.

##### cluster\_name

Deploys the component to every server instance in the cluster.

##### instance\_name

Deploys the component to a particular stand-alone sever instance.

#### --type

The packaging archive type of the component that is being deployed. Possible values are as follows:

##### car

The component is packaged as a CAR file.

##### ear

The component is packaged as an EAR file.

##### ejb

The component is an EJB packaged as a JAR file.

##### osgi

The component is packaged as an OSGi bundle.

**rar**

The component is packaged as a RAR file.

**war**

The component is packaged as a WAR file.

**--properties or --property**

Optional keyword-value pairs that specify additional properties for the deployment. The available properties are determined by the implementation of the component that is being deployed or redeployed. The **--properties** option and the **--property** option are equivalent. You can use either option regardless of the number of properties that you specify.

You can specify the following properties for a deployment:

**jar-signing-alias**

Specifies the alias for the security certificate with which the application client container JAR file is signed. Java Web Start will not run code that requires elevated permissions unless it resides in a JAR file signed with a certificate that the user's system trusts. For your convenience, Eclipse GlassFish signs the JAR file automatically using the certificate with this alias from the domain's keystore. Java Web Start then asks the user whether to trust the code and displays the Eclipse GlassFish certificate information. To sign this JAR file with a different certificate, add the certificate to the domain keystore, then use this property. For example, you can use a certificate from a trusted authority, which avoids the Java Web Start prompt, or from your own company, which users know they can trust. Default is **s1as**, the alias for the self-signed certificate created for every domain.

**java-web-start-enabled**

Specifies whether Java Web Start access is permitted for an application client module. Default is true.

**compatibility**

Specifies the Eclipse GlassFish release with which to be backward compatible in terms of JAR visibility requirements for applications. The only allowed value is **v2**, which refers to Sun GlassFish Enterprise Server version 2 or Sun Java System Application Server version 9.1 or 9.1.1. Beginning in Jakarta EE 6, the Jakarta EE platform specification imposed stricter requirements than Jakarta EE 5 did on which JAR files can be visible to various modules within an EAR file. In particular, application clients must not have access to EJB JAR files or other JAR files in the EAR file unless references use the standard Java SE mechanisms (extensions, for example) or the Jakarta EE library-directory mechanism. Setting this property to **v2** removes these restrictions.

**keepSessions={false|true}**

Superseded by the **--keepstate** option.

If the **--force** option is set to **true**, this property can be used to specify whether active sessions of the application that is being redeployed are preserved and then restored when the redeployment is complete. Applies to HTTP sessions in a web container. Default is **false**.

**false**

Active sessions of the application are not preserved and restored (default).

**true**

Active sessions of the application are preserved and restored.

If any active session of the application fails to be preserved or restored, none of the sessions will be available when the redeployment is complete. However, the redeployment continues and a warning is logged.

To preserve active sessions, Eclipse GlassFish serializes the sessions and saves them in memory. To restore the sessions, the class loader of the newly redeployed application deserializes any sessions that were previously saved.

**preserveAppScopedResources**

If set to `true`, preserves any application-scoped resources and restores them during redeployment. Default is `false`.

Other available properties are determined by the implementation of the component that is being redeployed.

For components packaged as OSGi bundles (`--type=osgi`), the `deploy` subcommand accepts properties arguments to wrap a WAR file as a WAB (Web Application Bundle) at the time of deployment. The subcommand looks for a key named `UriScheme` and, if present, uses the key as a URL stream handler to decorate the input stream. Other properties are used in the decoration process. For example, the Eclipse GlassFish OSGi web container registers a URL stream handler named `webbundle`, which is used to wrap a plain WAR file as a WAB. For more information about usage, see the example in this help page.

## Operands

**file\_archive|filepath**

The path to the archive that contains the application that is being deployed. This path can be a relative path or an absolute path.

The archive can be in either of the following formats:

- An archive file, for example, `/export/JEE_apps/hello.war`.  
If the `--upload` option is set to `true`, this is the path to the deployable file on the local client machine. If the `--upload` option is set to `false`, this is the path to the file on the server machine.
- A directory that contains the exploded format of the deployable archive. This is the path to the directory on the server machine.

If you specify a directory, the `--upload` option is ignored.

## Examples

## Example 1 Deploying an Enterprise Application

This example deploys the enterprise application packaged in the `Cart.ear` file to the default server instance `server`. You can use the `--target` option to deploy to a different server instance or to a cluster.

```
asadmin> deploy Cart.ear
Application deployed successfully with name Cart.
Command deploy executed successfully
```

## Example 2 Deploying a Web Application With the Default Context Root

This example deploys the web application in the `hello.war` file to the default server instance `server`. You can use the `--target` option to deploy to a different server instance or to a cluster.

```
asadmin> deploy hello.war
Application deployed successfully with name hello.
Command deploy executed successfully
```

## Example 3 Forcibly Deploying a Web Application With a Specific Context Root

This example forcibly deploys the web application in the `hello.war` file. The context root of the deployed web application is `greetings`. If the application has already been deployed, it is redeployed.

```
asadmin> deploy --force=true --contextroot greetings hello.war
Application deployed successfully with name hello.
Command deploy executed successfully
```

## Example 4 Deploying an Enterprise Bean

This example deploys a component based on the EJB specification (enterprise bean) with CMP and creates the database tables used by the bean.

This example uses the `--target` option. The target in this example is an existing cluster, `cluster1`.

```
asadmin> deploy --createtables=true --target cluster1 EmployeeEJB.jar
Application deployed successfully with name EmployeeEJB.
Command deploy executed successfully
```

## Example 5 Deploying a Connector Module

This example deploys a connector module that is packaged in a RAR file.

This example uses the `--target` option. The target in this example is an existing standalone server instance that does not belong to a cluster.

```
asadmin> deploy --target myinstance jdbcra.rar
Application deployed successfully with name jdbcra.
Command deploy executed successfully
```

## Example 6 Specifying the Deployment Order for an Application

This example specifies the deployment order for two applications. The `cart` application is loaded before the `horse` application at server startup.

Some lines of output are omitted from this example for readability.

```
asadmin> deploy --deploymentorder 102 --name cart cart.war
...
asadmin> deploy --deploymentorder 110 --name horse horse.war
...
```

## Example 7 Deploying an Application Using an Alternate Jakarta EE Deployment Descriptor File

This example deploys an application using a Jakarta EE standard deployment descriptor file that resides outside of the application archive.

```
asadmin> deploy --altdd path_to_alternate_descriptor cart.ear
Application deployed successfully with name cart.
Command deploy executed successfully
```

## Example 8 Deploying an Application Using an Alternate

Eclipse GlassFish Deployment Descriptor File

This example deploys an application using a Eclipse GlassFish runtime deployment descriptor file that resides outside of the application archive.

```
asadmin> deploy --runtimealtd path_to_alternate_runtime_descriptor horse.ear
Application deployed successfully with name horse.
Command deploy executed successfully
```

## Example 9 Wrapping a WAR File as a WAB

This example wraps a plain WAR file as a WAB when an OSGi bundle is deployed, and is specific to components packaged as OSGi bundles.

The backslash () character is used to escape characters in the command. For more information about escape characters in options for the [asadmin\(1M\)](#) utility, see the [asadmin\(1M\)](#) help page.

```
asadmin deploy --type osgi \
--properties "UriScheme=webbundle:Bundle-SymbolicName=bar:\
Import-Package=javax.servlet;javax.servlet.http;
%20version\\=3.0;resolution\\:
=mandatory:Web-ContextPath=/foo" \
/tmp/test_sample1.war
Application deployed successfully with name sample1.
Command deploy executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[get\(1\)](#), [list-components\(1\)](#), [redeploy\(1\)](#), [set\(1\)](#), [undeploy\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# deploydir

Deploys an exploded format of application archive

## Synopsis

```
asadmin [asadmin-options] deploydir [--help]
[--force={false|true}]
[--virtualservers virtual_servers]
[--contextroot context_root]
[--verify={false|true}]
[--precompilejsp={false|true}]
[--name component-name]
[--retrieve local_dirpath]
[--uniquetablenames={true|false}]
[--dbvendorname dbvendorname]
[--createtables={false|true}|--dropandcreatetables={false|true}]
[--deploymentplan deployment_plan]
[--altdd alternate_deploymentdescriptor]
[--runtimealtdd runtime_alternate_deploymentdescriptor]
[--deploymentorder deployment_order]
[--enabled={true|false}]
[--generatermistubs={false|true}]
[--availabilityenabled={false|true}]
[--asyncreplication={true|false}]
[--lbenabled={true|false}]
[--keepstate={false|true}]
[--libraries jar_file[,jar_file]*]
[--target target]
[--type pkg-type]
[--properties(name=value)[:name=value]*]
dirpath
```

## Description



The `deploydir` subcommand is deprecated. Use the `deploy` subcommand instead.

The `deploydir` subcommand deploys an application directly from a development directory. The appropriate directory hierarchy and deployment descriptors conforming to the Jakarta EE specification must exist in the deployment directory.

Directory deployment is for advanced developers only. Do not use `deploydir` in production environments. Instead, use the `deploy` subcommand. Directory deployment is only supported on localhost, that is, the client and server must reside on the same machine. For this reason, the only

values for the `--host` option are:

- `localhost`
- The value of the `$HOSTNAME` environment variable
- The IP address of the machine

If the `--uniquetablenames`, `--createtables`, and `--dropandcreatetables` options are not specified, the entries in the deployment descriptors are used.

The `--force` option makes sure the component is forcefully (re)deployed even if the specified component has already been deployed or already exists. Set the `--force` option to false for an initial deployment. If the specified application is running and the `--force` option is set to false, the subcommand fails.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### `--help`

`-?`

Displays the help text for the subcommand.

#### `--force`

If set to `true`, redeloys the component even if the specified component has already been deployed or already exists. Default is `false`.

#### `--virtualservers`

One or more virtual server IDs. Multiple IDs are separated by commas.

#### `--contextroot`

Valid only if the archive is a web module. It is ignored for other archive types; it will be the value specified by default-context-path in web.xml, if specified; defaults to filename without extension.

#### `--precompilejsp`

By default this option does not allow the JSP to be precompiled during deployment. Instead, JSPs are compiled during runtime. Default is `false`.

#### `--verify`

If set to true and the required verifier packages are installed from the Update Tool, the syntax and semantics of the deployment descriptor is verified. Default is `false`.

**--name**

Name of the deployable component.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see "[Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

**--retrieve**

Retrieves the client stub JAR file from the server machine to the local directory.

**--dbvendorname**

Specifies the name of the database vendor for which tables are created. Supported values include `db2`, `mssql`, `mysql`, `oracle`, `derby`, `javadb`, `postgresql`, and `sybase`. These values are case-insensitive. If not specified, the value of the `database-vendor-name` attribute in `glassfish-ejb-jar.xml` is used. If no value is specified, a connection is made to the resource specified by the `jndi-name` subelement of the `cmp-resource` element in the `glassfish-ejb-jar.xml` file, and the database vendor name is read. If the connection cannot be established, or if the value is not recognized, SQL-92 compliance is presumed.

**--createtables**

If specified as true, creates tables at deployment of an application with unmapped CMP beans. If specified as false, tables are not created. If not specified, the value of the `create-tables-at-deploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file determines whether or not tables are created. No unique constraints are created for the tables.

**--dropandcreatetables**

If specified as true when the component is redeployed, the tables created by the previous deployment are dropped before creating the new tables. Applies to deployed applications with unmapped CMP beans. Preexisting tables will not be dropped on the initial deployment of an application or on a deployment that follows an explicit undeploy. If specified as false, tables are neither dropped nor created. If not specified, the tables are dropped if the `drop-tables-at-undeploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file is set to true, and the new tables are created if the `create-tables-at-deploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file is set to true.

**--uniquetablename**

Guarantees unique table names for all the beans and results in a hash code added to the table names. This is useful if you have an application with case-sensitive bean names. Applies to applications with unmapped CMP beans.

**--deploymentplan**

Deploys the deployment plan, which is a JAR file that contains Eclipse GlassFish descriptors. Specify this option when deploying a pure EAR file. A pure EAR file is an EAR without Eclipse GlassFish descriptors.

**--altdd**

Deploys the application using a Jakarta EE standard deployment descriptor that resides outside of the application archive. Specify an absolute path or a relative path to the alternate deployment descriptor file. The alternate deployment descriptor overrides the top-level deployment descriptor packaged in the archive. For example, for an EAR, the `--altdd` option overrides `application.xml`. For a standalone module, the `--altdd` option overrides the top-level module descriptor such as `web.xml`.

**--runtimealtdd**

Deploys the application using a Eclipse GlassFish runtime deployment descriptor that resides outside of the application archive. Specify an absolute path or a relative path to the alternate deployment descriptor file. The alternate deployment descriptor overrides the top-level deployment descriptor packaged in the archive. For example, for an EAR, the `--runtimealtdd` option overrides `glassfish-application.xml`. For a standalone module, the `--runtimealtdd` option overrides the top-level module descriptor such as `glassfish-web.xml`. Applies to Eclipse GlassFish deployment descriptors only (`glassfish-.xml`); the name of the alternate deployment descriptor file must begin with `glassfish-`. Does not apply to `sun-.xml` deployment descriptors, which are deprecated.

**--deploymentorder**

Specifies the deployment order of the application. This is useful if the application has dependencies and must be loaded in a certain order at server startup. The deployment order is specified as an integer. The default value is 100. Applications with lower numbers are loaded before applications with higher numbers. For example, an application with a deployment order of 102 is loaded before an application with a deployment order of 110. If a deployment order is not specified, the default value of 100 is assigned. If two applications have the same deployment order, the first application to be deployed is the first application to be loaded at server startup.

The deployment order is typically specified when the application is first deployed but can also be specified or changed after initial deployment using the `set` subcommand. You can view the deployment order of an application using the `get` subcommand

**--enabled**

Allows users to access the application. If set to `false`, users will not be able to access the application. This option enables the application on the specified target instance or cluster. If you deploy to the target `domain`, this option is ignored, since deploying to the domain doesn't deploy to a specific instance or cluster. The default is `true`.

**--generatermi stubs**

If set to `true`, static RMI-IIOP stubs are generated and put into the `client.jar`. If set to `false`, the stubs are not generated. Default is `false`.

**--availabilityenabled**

This option controls whether high-availability is enabled for web sessions and for stateful session bean (SFSB) checkpointing and potentially passivation. If set to false (default) all web session saving and SFSB checkpointing is disabled for the specified application, web application, or EJB module. If set to true, the specified application or module is enabled for high-availability. Set this option to true

only if high availability is configured and enabled at higher levels, such as the server and container levels.

#### --asyncreplication

This option controls whether web session and SFSB states for which high availability is enabled are first buffered and then replicated using a separate asynchronous thread. If set to true (default), performance is improved but availability is reduced. If the instance where states are buffered but not yet replicated fails, the states are lost. If set to false, performance is reduced but availability is guaranteed. States are not buffered but immediately transmitted to other instances in the cluster.

#### --lbenabled

This option controls whether the deployed application is available for load balancing. The default is true.

#### --keepstate

- This option controls whether web sessions, SFSB instances, and persistently created EJB timers are retained between redeployments. The default is false. This option is supported only on the default server instance, named `server`. It is not supported and ignored for any other target.
- Some changes to an application between redeployments prevent this feature from working properly. For example, do not change the set of instance variables in the SFSB bean class. For web applications, this feature is applicable only if in the `glassfish-web-app.xml` file the `persistence-type` attribute of the `session-manager` element is `file`.
- For stateful session bean instances, the persistence type without high availability is set in the server (the `sfsb-persistence-type` attribute) and must be set to `file`, which is the default and recommended value.
- If any active web session, SFSB instance, or EJB timer fails to be preserved or restored, none of these will be available when the redeployment is complete. However, the redeployment continues and a warning is logged.
- To preserve active state data, Eclipse GlassFish serializes the data and saves it in memory. To restore the data, the class loader of the newly redeployed application deserializes the data that was previously saved.

#### --libraries

A comma-separated list of library JAR files. Specify the library JAR files by their relative or absolute paths. Specify relative paths relative to domain-dir `lib/applibs`. The libraries are made available to the application in the order specified.

#### --target

Specifies the target to which you are deploying. Valid values are:

##### `server`

Deploys the component to the default server instance `server` and is the default value.

**domain**

Deploys the component to the domain. If **domain** is the target for an initial deployment, the application is deployed to the domain, but no server instances or clusters reference the application. If **domain** is the target for a redeployment (the **--force** option is set to true), and dynamic reconfiguration is enabled for the clusters or server instances that reference the application, the referencing clusters or server instances automatically get the new version of the application. If redeploying, and dynamic configuration is disabled, the referencing clusters or server instances do not get the new version of the application until the clustered or standalone server instances are restarted.

**cluster\_name**

Deploys the component to every server instance in the cluster.

**instance\_name**

Deploys the component to a particular stand-alone server instance.

**--type**

The packaging archive type of the component that is being deployed. Possible values are as follows:

**car**

The component is packaged as a CAR file.

**ear**

The component is packaged as an EAR file.

**ejb**

The component is an EJB packaged as a JAR file.

**osgi**

The component is packaged as an OSGi bundle.

**rar**

The component is packaged as a RAR file.

**war**

The component is packaged as a WAR file.

**--properties or --property**

Optional keyword-value pairs that specify additional properties for the deployment. The available properties are determined by the implementation of the component that is being deployed or redeployed. The **--properties** option and the **--property** option are equivalent. You can use either option regardless of the number of properties that you specify.

You can specify the following properties for a deployment:

## **jar-signing-alias**

Specifies the alias for the security certificate with which the application client container JAR file is signed. Java Web Start will not run code that requires elevated permissions unless it resides in a JAR file signed with a certificate that the user's system trusts. For your convenience, Eclipse GlassFish signs the JAR file automatically using the certificate with this alias from the domain's keystore. Java Web Start then asks the user whether to trust the code and displays the Eclipse GlassFish certificate information. To sign this JAR file with a different certificate, add the certificate to the domain keystore, then use this property. For example, you can use a certificate from a trusted authority, which avoids the Java Web Start prompt, or from your own company, which users know they can trust. Default is `s1as`, the alias for the self-signed certificate created for every domain.

## **java-web-start-enabled**

Specifies whether Java Web Start access is permitted for an application client module. Default is true.

## **compatibility**

Specifies the Eclipse GlassFish release with which to be backward compatible in terms of JAR visibility requirements for applications. The only allowed value is `v2`, which refers to Sun GlassFish Enterprise Server version 2 or Sun Java System Application Server version 9.1 or 9.1.1. Beginning in Jakarta EE 6, the Jakarta EE platform specification imposed stricter requirements than Jakarta EE 5 did on which JAR files can be visible to various modules within an EAR file. In particular, application clients must not have access to EJB JAR files or other JAR files in the EAR file unless references use the standard Java SE mechanisms (extensions, for example) or the Jakarta EE library-directory mechanism. Setting this property to `v2` removes these restrictions.

## **keepSessions={false|true}**

Superseded by the `--keepstate` option.

If the `--force` option is set to `true`, this property can be used to specify whether active sessions of the application that is being redeployed are preserved and then restored when the redeployment is complete. Applies to HTTP sessions in a web container. Default is

**false**.

**false**

Active sessions of the application are not preserved and restored (default).

**true**

Active sessions of the application are preserved and restored.

If any active session of the application fails to be preserved or restored, none of the sessions will be available when the redeployment is complete. However, the redeployment continues and a warning is logged.

To preserve active sessions, Eclipse GlassFish serializes the sessions and saves them in memory. To restore the sessions, the class loader of the newly redeployed application deserializes any sessions that were previously saved.

**preserveAppScopedResources**

If set to `true`, preserves any application-scoped resources and restores them during redeployment. Default is `false`.

Other available properties are determined by the implementation of the component that is being redeployed.

For components packaged as OSGi bundles (`--type=osgi`), the `deploy` subcommand accepts properties arguments that can be used to wrap a WAR file as a WAB (Web Application Bundle). The subcommand looks for a key named `UriScheme` and, if present, uses the key as a URL stream handler to decorate the input stream. Other properties are used in the decoration process. The Eclipse GlassFish OSGi web container registers a URL stream handler named `webbundle`, which is used to wrap a plain WAR file as a WAB. For more information about usage, see the related example in the [deploy\(1\)](#) help page.

## Operands

**dirpath**

Path to the directory containing the exploded format of the deployable archive. This is the path to the directory on the server machine.

## Examples

### Example 1 Deploying an Application From a Directory

In this example, the exploded application to be deployed is in the `/home/temp/sampleApp` directory. Because the `--force` option is set to true, if an application of that name already exists, the application is redeployed.

```
asadmin> deploydir --force=true --precompilejsp=true /home/temp/sampleApp
Application deployed successfully with name sampleApp.
WARNING : deploydir command deprecated. Please use deploy command instead.
Command deploydir executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[get\(1\)](#), [deploy\(1\)](#), [redeploy\(1\)](#), [set\(1\)](#), [undeploy\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# disable

Disables the component

## Synopsis

```
asadmin [asadmin-options] disable [--help]
[--target target_name] component_name
```

## Description

The **disable** subcommand immediately disables the specified deployed component. If the component has not been deployed, an error message is returned.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target on which you are disabling the component. Valid values are:

##### server

Disables the component on the default server instance **server** and is the default value.

##### domain\_name

Disables the component on the named domain.

##### cluster\_name

Disables the component on every server instance in the cluster.

##### instance\_name

Disables the component on a particular clustered or stand-alone server instance.

# Operands

## component\_name

name of the component to be disabled.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. To disable multiple versions, you can use an asterisk (\*) as a wildcard character. For more information about module and application versions, see "Module and Application Versions" in Eclipse GlassFish Application Deployment Guide.

## Examples

### Example 1 Disabling a Component

This example disables the deployed component sampleApp.

```
asadmin> disable sampleApp  
Command disable executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[deploy\(1\)](#), [enable\(1\)](#), [undeploy\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# disable-http-lb-application

Disables an application managed by a load balancer

## Synopsis

```
asadmin [asadmin-options] disable-http-lb-application [--help]
[--timeout 30]
--name application_name target
```

## Description

The disable **disable-http-lb-application** subcommand disables an application for load balancing. The disabled application goes offline for load balancing with minimal impact to users. Disabling an application gives a finer granularity of control than disabling a server instance and is most useful when a cluster is hosting multiple independent applications.

Once the application is disabled and the changes have been applied to the load balancer, new requests for the application are not forwarded to the target. Existing sessions continue to access the application until the timeout is reached. This process is known as quiescing.

If an application is deployed across multiple clusters, use this subcommand to disable it in one cluster while leaving it enabled in others.

If an application is deployed to a single server instance, use this subcommand to disable it in that instance while leaving the instance itself enabled.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--timeout**

The timeout (in minutes) to wait before disabling the specified application. This time allows for the graceful shutdown (quiescing) of the specified application. The default value is 30 minutes. The

minimum value is 1 minute.

#### --name

The name of the application to be disabled.

## Operands

### target

This operand specifies the server instance or cluster on which to disable the application. Valid values are:

- cluster\_name- The name of a target cluster.
- instance\_name- The name of a target server instance.

## Examples

### Example 1 Disabling an Application for Load Balancing

This example, disables an application for load balancing

```
asadmin> disable-http-lb-application --name webapps-simple mycluster
```

```
Command disable-http-lb-application executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[enable-http-lb-application\(1\)](#)

# disable-http-lb-server

Disables a sever or cluster managed by a load balancer

## Synopsis

```
asadmin [asadmin-options] disable-http-lb-server [--help]
[--timeout 30]
target
```

## Description

The **disable-http-lb-server** subcommand disables a standalone server or cluster of servers for load balancing. The disabled server instance or cluster goes offline for load balancing with a minimum impact to users.

Once the target has been disabled and the changes have been applied to the load balancer, the load balancer stops assigning new requests to the target. Session requests with sessions created before disabling the target continue to be assigned to that target until the timeout is reached. This process is known as quiescing.

Changes are applied the load balancer automatically. You can also manually export the configuration using **export-http-lb-config** and copy it to the load balancer.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--timeout**

The timeout (in minutes) to wait before disabling the specified target. This time allows for the graceful shutdown (quiescing) of the specified target. The default value is 30 minutes. The minimum value is 1 minute.

# Operands

## target

This operand specifies which server instances and clusters to disable. Valid values are:

- cluster\_name- The name of a target cluster.
- instance\_name- The name of a target server instance.

# Examples

## Example 1 Disabling a Cluster for Load Balancing

This example disables load balancing for a cluster named `mycluster`.

```
asadmin> disable-http-lb-server mycluster  
Command disable-http-lb-server executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-http-lb-ref\(1\)](#), [enable-http-lb-server\(1\)](#)

# disable-monitoring

Disables monitoring for the server or for specific monitorable modules

## Synopsis

```
asadmin [asadmin-options] disable-monitoring [--help]
[--modules module-name][:module-name]*
```

## Description

The **disable-monitoring** subcommand is used to turn off monitoring for Eclipse GlassFish or for particular modules during runtime. Changes are dynamic, that is, server restart is not required.

Running the **disable-monitoring** subcommand without the **--module** option disables the monitoring service by setting the **monitoring-enabled** attribute of the **monitoring-service** element to **false**. The individual modules retain their monitoring levels, but no monitoring data is generated because the entire monitoring service is disabled.

This subcommand used with the **--modules** option disables monitoring for a module by setting the monitoring level to OFF. The status of the monitoring service is not affected. For a list of monitorable modules, see the **--modules** option in this help page.

An alternative method for disabling monitoring is to use the **set** subcommand. In this case, the server must be restarted for changes to take effect.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --modules

Disables the specified module or modules by setting the monitoring level to OFF. Multiple modules are separated by : (colon). Monitorable modules include **connector-connection-pool**, **connector-service**, **ejb-container**, **http-service**, **jdbc-connection-pool**, **jersey**, **jpa**, **jms-service**, **jvm**, **security**, **thread-pool**, **transaction-service**, **web-container**, and **web-services-container**. Additional modules

can be listed by using the `get` subcommand.

## Operands

## Examples

### Example 1 Disabling the Monitoring Service for Eclipse GlassFish

This example disables monitoring for Eclipse GlassFish in general by setting the `enable-monitoring` flag to `false` (default is `true`).

```
asadmin> disable-monitoring  
Command disable-monitoring executed successfully
```

### Example 2 Disabling Monitoring for the Web and EJB Containers

This example disables monitoring for specific containers. Their monitoring levels will be set to OFF.

```
asadmin> disable-monitoring --modules web-container:ejb-container  
Command disable-monitoring executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[get\(1\)](#), [enable-monitoring\(1\)](#), [list\(1\)](#), [monitor\(1\)](#), [set\(1\)](#)

[monitoring\(5ASC\)](#)

"[Administering the Monitoring Service](#)" in Eclipse GlassFish Administration Guide



# disable-secure-admin

Disables secure admin if it is already enabled.

## Synopsis

```
asadmin [asadmin-options] disable-secure-admin [--help]
```

## Description

The **disable-secure-admin** subcommand disables secure admin if it is already enabled.



You must restart any running servers in the domain after you enable or disable secure admin. It is simpler to enable or disable secure admin with only the DAS running, then restart the DAS, and then start any other instances.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Examples

### Example 1 Disabling **secure admin** for a domain

The following example shows how to disable **secure admin** for a domain.

```
asadmin> disable-secure-admin  
server-config  
default-config  
  
Command disable-secure-admin executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[enable-secure-admin\(1\)](#)

# disable-secure-admin-internal-user

Instructs the Eclipse GlassFish DAS and instances to not use the specified admin user to authenticate with each other and to authorize admin operations.

## Synopsis

```
asadmin [asadmin-options] disable-secure-admin-internal-user [--help]  
admin-username
```

## Description

The **disable-secure-admin-internal-user** subcommand disables secure admin from using the username (instead of SSL certificates) to authenticate the DAS and instances with each other and to authorize admin operations.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### admin-username

The admin user name that Eclipse GlassFish should not use to authenticate the DAS and instances with each other and to authorize admin operations.

## Examples

### Example 1 Disabling a user name for secure admin

The following example disables secure admin from using username tester to authenticate the DAS and instances with each other and to authorize admin operations.

```
asadmin> disable-secure-admin-internal-user tester
```

```
Command disable-secure-admin-internal-user executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[enable-secure-admin\(1\)](#), [enable-secure-admin-internal-user\(1\)](#)

# disable-secure-admin-principal

Disables the certificate for authorizing access in secure administration.

## Synopsis

```
asadmin [asadmin-options] disable-secure-admin-principal [--help]
--alias aliasname | DN
```

## Description

The **disable-secure-admin-principal** subcommand disables the certificate as being valid for authorizing access as part of secure administration.

You must specify either the **--alias** option, or the DN.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

### --alias

The alias name of the certificate in the truststore. Eclipse GlassFish looks up the certificate in the truststore using that alias and, if found, disables the corresponding DN as being valid for secure administration. Because alias-name must be an alias associated with a certificate currently in the truststore, you may find it most useful for self-signed certificates.

## Operands

### DN

The distinguished name of the certificate, specified as a comma-separated list in quotes. For example, "CN=system.amer.oracle.com,OU=GlassFish,O=Oracle Corporation,L=Santa Clara,ST=California,C=US".

## Examples

## Example 1 Disables trust of a DN for secure administration

The following example shows how to disable trust of a DN for authorizing access in secure administration.

```
asadmin> disable-secure-admin-principal  
"CN=system.amer.oracle.com,OU=GlassFish,  
O=Oracle Corporation,L=Santa Clara,ST=California,C=US"
```

Command disable-secure-admin-principal executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[enable-secure-admin\(1\)](#), [enable-secure-admin-principal\(1\)](#)

# enable

Enables the component

## Synopsis

```
asadmin [asadmin-options] enable [--help]
[--target target_name] component_name
```

## Description

The **enable** subcommand enables the specified deployed component. If the component is already enabled, then it is re-enabled. If it has not been deployed, then an error message is returned.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target on which you are enabling the component. Valid values are:

##### server

Enables the default server instance **server** and is the default value.

##### domain\_name

Enables the named domain.

##### cluster\_name

Enables every server instance in the cluster.

##### instance\_name

Enables a particular clustered or stand-alone server instance.

# Operands

## **component\_name**

name of the component to be enabled.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see " [Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

At most one version of a module or application can be enabled on a server instance. All other versions are disabled. Enabling one version automatically disables all others.

## Examples

### Example 1 Enabling a Component

This example enables the disabled component, `sampleApp`.

```
asadmin> enable sampleApp
Command enable executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[deploy\(1\)](#), [disable\(1\)](#), [undeploy\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# enable-http-lb-application

Enables a previously-disabled application managed by a load balancer

## Synopsis

```
asadmin [asadmin-options] enable-http-lb-application [--help]
--name application_name target
```

## Description

The **enable-http-lb-application** subcommand enables load balancing for applications deployed on a standalone instance or cluster. You can enable load balancing for an application on all instances in a cluster, or on a single standalone server instance. By default, load balancing is enabled for applications.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--name**

The name of the application to be enabled.

## Operands

### target

This operand specifies on which server instance or cluster to enable the application. Valid values are:

- `cluster_name`- The name of a target cluster.
- `instance_name`- The name of a target server instance.

# Examples

## Example 1 Enabling Load Balancing for an Application

This example enables an application named `webapps-simple` to use load balancing on a cluster named `mycluster`.

```
asadmin> enable-http-lb-application --name webapps-simple mycluster
```

```
Command enable-http-lb-application executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[disable-http-lb-application\(1\)](#)

# enable-http-lb-server

Enables a previously disabled sever or cluster managed by a load balancer

## Synopsis

```
asadmin [asadmin-options] enable-http-lb-server [--help]
target
```

## Description

The `enable-http-lb-server` subcommand enables a standalone server instance or cluster for load balancing. By default, load balancing is enabled for instances and clusters.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### target

This operand specifies which server instances and clusters to enable. Valid values are:

- `cluster_name`- The name of a target cluster.
- `instance_name`- The name of a target server instance.

## Examples

## Example 1 Enabling a Cluster for Load Balancing

This example enables load balancing for a cluster named `mycluster`.

```
asadmin> enable-http-lb-server mycluster  
Command enable-http-lb-server executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb-ref\(1\)](#), [disable-http-lb-server\(1\)](#)

# enable-monitoring

Enables monitoring for the server or for specific monitorable modules

## Synopsis

```
asadmin [asadmin-options] enable-monitoring [--help]
[--target target]
[--mbean={false|true}]
[--dtrace={true|false}]
[--modules modules[=level][:module[=level]]*]
[--pid pid]
[--options options]]
```

## Description

The `enable-monitoring` subcommand is used to turn on monitoring for Eclipse GlassFish or for particular modules during runtime. Changes are dynamic, that is, server restart is not required.

By default, the monitoring service is enabled, that is, the `monitoring-enabled` attribute of the `monitoring-service` element is `true`. However, the default monitoring level for individual modules is `OFF`. This subcommand used with the `--modules` option can enable monitoring for a given module by setting the monitoring level to `HIGH` or `LOW`. If level is not specified when running the subcommand, the level defaults to `HIGH`.

The specific meanings of `HIGH` or `LOW` are determined by the individual containers. For a list of monitorable modules, see the `--modules` option in this help page.

An alternative method for enabling monitoring is to use the `set` subcommand. In this case, the server must be restarted for changes to take effect.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--target**

Specifies the target on which to enabling monitoring. Valid values are as follows:

**server**

Enables monitoring for the default server instance **server** and is the default value.

**configuration-name**

Enables monitoring for the named configuration.

**cluster-name**

Enables monitoring for every server instance in the cluster.

**instance-name**

Enables monitoring for a particular server instance.

**--mbean**

Enables Mbean monitoring. Default value is false.

**--dtrace**

Only usable if the DTrace Monitoring module is present. Enables Oracle Solaris DTrace monitoring. Default value is false.

**--modules**

Enables specified module or modules by indicating monitoring level. Valid levels are OFF, HIGH, LOW. If level is not specified, the default setting is HIGH. Multiple modules are separated by : (colon). Monitorable modules include **connector-connection-pool**, **connector-service**, **ejb-container**, **http-service**, **jdbc-connection-pool**, **jersey**, **jpa**, **jms-service**, **jvm**, **security**, **thread-pool**, **transaction-service**, **web-container**, and **web-services-container**. Additional modules can be listed by using the **get** subcommand.

**--pid**

Specifies the Eclipse GlassFish JVM process identifier (PID). When monitoring is enabled, the **btrace-agent** is attached, based on the specified PID. Need to specify only in exceptional cases when the system cannot determine the PID. In this situation, the subcommand prompts for the PID of the corresponding Eclipse GlassFishprocess.

**--options**

Sets the following **btrace-agent** options:

**debug**

Enables debugging for BTrace. Default value is false.

# Examples

## Example 1 Enabling the Monitoring Service for Eclipse GlassFish

This example enables monitoring for Eclipse GlassFish in general by setting the `enable-monitoring` flag to `true` (default is `true`).

```
asadmin> enable-monitoring
Command enable-monitoring executed successfully
```

## Example 2 Enabling Monitoring for the Web and EJB Containers

This example enables monitoring for specific containers by setting their monitoring levels.

```
asadmin> enable-monitoring --modules web-container=LOW:ejb-container=HIGH
Command enable-monitoring executed successfully
```

## Example 3 Turning on Debugging for Monitoring

This example turns on debugging.

```
asadmin> enable-monitoring --options debug=true
Command enable-monitoring executed successfully
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[disable-monitoring\(1\)](#), [get\(1\)](#), [list\(1\)](#), [monitor\(1\)](#), [set\(1\)](#)

[monitoring\(5ASC\)](#)

"[Administering the Monitoring Service](#)" in Eclipse GlassFish Administration Guide

# enable-secure-admin

Enables secure admin (if it is not already enabled), optionally changing the alias used for DAS-to-instance admin messages or the alias used for instance-to-DAS admin messages.

## Synopsis

```
asadmin [asadmin-options] enable-secure-admin [--help]
[--adminalias=alias]
[--instancealias=alias]
```

## Description

The `enable-secure-admin` subcommand causes the DAS and the instances in the domain to use SSL certificates for encrypting the messages they send to each other. This subcommand also allows the DAS to accept administration messages from remote admin clients such as the `asadmin` utility and IDEs.



You must restart any running servers in the domain after you enable or disable secure admin. It is simpler to enable or disable secure admin with only the DAS running, then restart the DAS, and then start any other instances.

By default, when secure admin is enabled the DAS and the instances use these SSL certificates to authenticate to each other as security "principals" and to authorize admin access. The `--asadminalias` value indicates to the DAS which SSL certificate it should use to identify itself to the instances. The `--instancealias` value determines for instances which SSL certificate they should use to identify themselves to the DAS.

The `enable-secure-admin` subcommand fails if any administrative user in the domain has a blank password.

Alternatively, you can use the `enable-secure-admin-internal-user` subcommand to cause the servers to identify themselves using a secure admin user name and password.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--adminalias**

The alias that refers to the SSL/TLS certificate on the DAS. This alias is used by the DAS to identify itself to instances. The default value is `s1as`.

**--instancealias**

The alias that refers to the SSL/TLS certificate on the instances. This alias is used by the instances to identify themselves to the DAS. The default value is `glassfish-instance`.

## Examples

### Example 1 Enabling `secure admin` for a domain

The following example shows how to enable `secure admin` for a domain using an admin alias `adtest` and an instance alias `intest`

```
asadmin> enable-secure-admin --adminalias adtest --instancealias intest
server-config
default-config
```

Command `enable-secure-admin` executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[disable-secure-admin\(1\)](#), [enable-secure-admin-principal\(1\)](#), [enable-secure-admin-internal-user\(1\)](#)

# enable-secure-admin-internal-user

Instructs the Eclipse GlassFish DAS and instances to use the specified admin user and the password associated with the password alias to authenticate with each other and to authorize admin operations.

## Synopsis

```
asadmin [asadmin-options] enable-secure-admin-internal-user [--help]
[--passwordalias pwdaliasname]
admin-username
```

## Description

The `enable-secure-admin-internal-user` subcommand instructs all servers in the domain to authenticate to each other, and to authorize admin operations submitted to each other, using an existing admin username and password rather than SSL certificates. This generally means that you must:

1. Create a valid admin user.

```
asadmin> create-file-user --authrealmname admin-realm --groups
asadmin newAdminUsername
```

2. Create a password alias for the just-created password.

```
asadmin> create-password-alias passwordAliasName
```

3. Use that user name and password for inter-process authentication and admin authorization.

```
asadmin> enable-secure-admin-internal-user
--passwordalias passwordAliasName
newAdminUsername
```

If Eclipse GlassFish finds at least one secure admin internal user, then if secure admin is enabled Eclipse GlassFish processes will not use SSL authentication and authorization with each other and will instead use username password pairs.

If secure admin is enabled, all Eclipse GlassFish processes continue to use SSL encryption to secure the content of the admin messages, regardless of how they authenticate to each other.

Most users who use this subcommand will need to set up only one secure admin internal user. As a general practice, you should not use the same user name and password pair for internal admin communication and for admin user login.

If you set up more than one secure admin internal user, you should not make any assumptions about which user name and password pair Eclipse GlassFish will choose to use for any given admin request.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

### `--passwordalias`

The password alias for the user that Eclipse GlassFish should use for internally authenticating and authorizing the DAS to instances and the instances to the DAS.

## Operands

### admin-username

The admin user name that Eclipse GlassFish should use for internally authenticating and authorizing the DAS to instances and the instances to the DAS.

## Examples

### Example 1 Specifying a user name and password for secure admin

The following example allows secure admin to use a user name and password alias for authentication and authorization between the DAS and instances, instead of certificates.

```
asadmin> enable-secure-admin-internal-user
--passwordalias passwordAliasName
newAdminUsername
```

## Exit Status

---

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[disable-secure-admin-internal-user\(1\)](#), [enable-secure-admin\(1\)](#)

# enable-secure-admin-principal

Instructs Eclipse GlassFish, when secure admin is enabled, to accept admin requests from clients identified by the specified SSL certificate.

## Synopsis

```
asadmin [asadmin-options] enable-secure-admin-principal [--help]
--alias aliasname | DN
```

## Description

The `enable-secure-admin-principal` subcommand instructs Eclipse GlassFish to accept admin requests when accompanied by an SSL certificate with the specified distinguished name (DN). If you use the "`--alias` aliasname`" form, then Eclipse GlassFish looks in its truststore for a certificate with the specified alias and uses the DN associated with that certificate. Otherwise, Eclipse GlassFish records the value you specify as the DN.

You must specify either the `--alias` option, or the DN.

You can run `enable-secure-admin-principal` multiple times so that Eclipse GlassFish accepts admin requests from a client sending a certificate with any of the DNs you specify.

When you run `enable-secure-admin`, Eclipse GlassFish automatically records the DNs for the admin alias and the instance alias, whether you specify those values or use the defaults. You do not need to run `enable-secure-admin-principal` yourself for those certificates. Other than these certificates, you must run `enable-secure-admin-principal` for any other DN that Eclipse GlassFish should authorize to send admin requests. This includes DNs corresponding to trusted certificates (those with a certificate chain to a trusted authority.)

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --alias

The alias name of the certificate in the trust store. Eclipse GlassFish looks up certificate in the trust store using that alias and, if found, stores the corresponding DN as being valid for secure

administration. Because alias-name must be an alias associated with a certificate currently in the trust store, you may find it most useful for self-signed certificates.

## Operands

### DN

The distinguished name of the certificate, specified as a comma-separated list in quotes. For example, "CN=system.amer.oracle.com,OU=GlassFish,O=Oracle Corporation,L=Santa Clara,ST=California,C=US".

## Examples

### Example 1 Trusting a DN for secure administration

The following example shows how to specify a DN for authorizing access in secure administration.

```
asadmin> enable-secure-admin-principal  
"CN=system.amer.oracle.com,OU=GlassFish,  
O=Oracle Corporation,L=Santa Clara,ST=California,C=US"
```

Command enable-secure-admin-principal executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[disable-secure-admin-principal\(1\)](#), [enable-secure-admin\(1\)](#)

# export

Marks a variable name for automatic export to the environment of subsequent commands in multimode

## Synopsis

```
asadmin [asadmin-options] export [--help]
[variable-name=value [variable-name=value]*]
```

## Description

In multimode, the **export** subcommand marks an environment variable for automatic export to the environment of subsequent commands. All subsequent commands use the variable name value as specified unless you exit multimode, or use the **unset** subcommand to unset the variable. If only the variable name is specified, the current value of that variable name is displayed.

If the **export** subcommand is used without any arguments, a list of all the exported variables and their values is displayed. Exported shell environment variables set prior to invoking the **asadmin** utility are imported automatically and set as exported variables within **asadmin**. Environment variables that are not exported cannot be read by the **asadmin** utility.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### variable-name=value

Variable name and value for automatic export to the environment to be used by subsequent commands.

# Examples

## Example 1 Listing the Environment Variables That Are Set

This example lists the environment variables that have been set.

```
asadmin> export
AS_ADMIN_USER = admin
AS_ADMIN_HOST = bluestar
AS_ADMIN_PREFIX = server1.jms-service
AS_ADMIN_PORT = 8000
Command export executed successfully
```

## Example 2 Setting an Environment Variable

This example sets the `AS_ADMIN_HOST` environment variable to `bluestar`.

```
asadmin> export AS_ADMIN_HOST=bluestar
Command export executed successfully
```

## Example 3 Setting Multiple Environment Variables

This example sets a number of environment variables for the multimode environment.

```
asadmin> export AS_ADMIN_HOST=bluestar AS_ADMIN_PORT=8000
AS_ADMIN_USER=admin AS_ADMIN_PREFIX=server1.jms-service
Command export executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[multimode\(1\)](#), [unset\(1\)](#)

# export-http-lb-config

Exports the load balancer configuration or load balancer to a file

## Synopsis

```
asadmin [asadmin-options] export-http-lb-config [--help]
--config config_name | --lbname load_balancer_name
[--target target] [--retrievefile=false] [file_name]
```

## Description

The `export-http-lb-config` subcommand exports a load balancer configuration or load balancer into a file that the load balancer plug-in can use. The default file name is `loadbalancer.xml`, but you can specify a different name. Once exported, you manually copy the exported file to the load balancer plug-in location before configuration changes are applied. The `--target` option makes it possible to generate a `loadbalancer.xml` for clusters or standalone instances without having to manually create `lb-config` or `load-balancer` elements in the target's `domain.xml`.

To apply changes to the load balancer without manually copying the configuration file, configure the load balancer to automatically apply changes with `create-http-lb`. If you use the `create-http-lb` subcommand, you do not need to use `export-http-lb-config`.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--config**

Specifies which load balancer configuration to export.

Specify either a load balancer configuration or a load balancer. Specifying both results in an error.

**--lbname**

Specifies the load balancer to export.

Specify either a load balancer configuration or a load balancer. Specifying both results in an error.

#### --retrievefile

If set to `true`, retrieves the `loadbalancer.xml` file from the remote machine. The default is `false`.

#### --target

Specifies the target to which the load balancer configuration will be exported. If a target is not specified, the load balancer configuration is exported to the location specified with `file_name`.

## Operands

### file\_name

Specifies the file name and location of the exported configuration.

- If you specify a directory (relative or absolute) but not a file name, the file named `loadbalancer.xml.``load_balancer_config_name` is created in the specified directory. On Microsoft Windows systems the path must be in quotes.
- If you specify a file name in a relative or absolute path, the file is created with the name you specify in the directory you specify.
- If you specify a file name but do not specify a directory, the file is created with that name in the current working directory.
- If you do not specify this operand, the default value is a file named `loadbalancer.xml.``load_balancer_config_name` created in the domain-dir/`generated` directory.

### target

Specifies the target to which the configuration will be exported.

Valid values are:

- `cluster_name`- Specifies a cluster and its server instances.
- `stand-alone_instance_name`- Specifies a specific server instance.

## Examples

### Example 1 Exporting a Load Balancer Configuration on UNIX

The following example exports a load balancing configuration named `mycluster-http-lb-config` to a file named `loadbalancer.xml` in the `/Sun/AppServer` directory .

```
asadmin> export-http-lb-config --config mycluster-http-lb-config  
/Sun/AppServer/loadbalancer.xml  
Command export-http-lb-config executed successfully.
```

## Example 2 Exporting a Load Balancer Configuration on Windows

The following example exports a load balancing configuration named `mycluster-http-lb-config` to a file named `loadbalancer.xml` in the `C:\Sun\AppServer` directory on a Microsoft Windows system.

```
asadmin> export-http-lb-config --config mycluster-http-lb-config  
"C:\Sun\AppServer\loadbalancer.xml"  
Command export-http-lb-config executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb\(1\)](#), [create-http-lb-config\(1\)](#), [list-http-lb-configs\(1\)](#)

# export-sync-bundle

Exports the configuration data of a cluster or standalone instance to an archive file

## Synopsis

```
asadmin [asadmin-options] export-sync-bundle [--help]
--target target
[--retrieve={false|true}]
[file-name]
```

## Description

The [export-sync-bundle](#) subcommand exports the configuration data of a cluster or standalone instance to an archive file. The archive file can then be used with the [import-sync-bundle\(1\)](#) subcommand to restore the configuration data.

Importing an instance's configuration data transfers the data to a host for an instance without the need for the instance to be able to communicate with the domain administration server (DAS). Importing an instance's configuration data is typically required for the following reasons:

- To reestablish the instance after an upgrade
- To synchronize the instance manually with the DAS when the instance cannot contact the DAS

The subcommand creates an archive that contains the following files and directories in the current domain directory:

- All the files in the following directories:
  - [config](#)
  - [docroot](#)
- The entire contents of the following directories and their subdirectories:
  - [applications](#)
  - [config](#)/target, where target is the cluster or standalone instance for which configuration data is being exported
  - [generated](#)
  - [lib](#)

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

`-?`

Displays the help text for the subcommand.

### --target

The cluster or standalone instance for which to export configuration data. The `--target` option is required.

This option must not specify a clustered Eclipse GlassFish instance. If this option specifies a clustered instance, an error occurs. To export configuration data for a clustered instance, specify the name of the cluster of which the instance is a member, not the instance.

### --retrieve

Specifies whether the archive file is downloaded from the DAS host to the host where the subcommand is run. Possible values are as follows:

`true`

The archive file is downloaded to the host where the subcommand is run.

`false`

The archive file is not downloaded and remains on the DAS host (default).

# Operands

## file-name

The file name and location of the archive file to which to export the data. The default depends on the setting of the `--retrieve` option:

- If `--retrieve` is `false`, the default is `sync/`target-sync-bundle.zip`` in the current domain directory.
- If `--retrieve` is `true`, the default is `target-sync-bundle.zip` in the current working directory. `target` is the cluster or standalone instance that the `--target` option specifies.  
If a relative path is specified, the directory to which the path is appended depends on the setting of the `--retrieve` option:
  - If `--retrieve` is `false`, the path is appended to the `config` subdirectory of the current domain directory.
  - If `--retrieve` is `true`, the path is appended to the current working directory.

If an existing directory is specified without a filename, the file name of the archive file is `target-sync`

`-bundle.zip`, where target is the cluster or standalone instance that the `--target` option specifies.

## Examples

### Example 1 Exporting the Configuration Data of a Cluster

This example exports the configuration data of the cluster `pmdcluster`.

```
asadmin> export-sync-bundle --target=pmdcluster
Sync bundle: /export/glassfish7/glassfish/domains/domain1-sync/
pmdcluster-sync-bundle.zip
```

Command `export-sync-bundle` executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[import-sync-bundle\(1\)](#)

# flush-connection-pool

Reinitializes all connections established in the specified connection pool

## Synopsis

```
asadmin [asadmin-options] flush-connection-pool [--help]
[--appname application [--modulename module]
pool_name
```

## Description

The **flush-connection-pool** subcommand resets a JDBC connection pool or a connector connection pool to its initial state. Any existing live connections are destroyed, which means that the transactions associated with these connections are lost. The subcommand then recreates the initial connections for the pool, and restores the pool to its steady pool size.

This subcommand is supported in remote mode only.

### Application Scoped Resources

The **flush-connection-pool** subcommand can target resources that are scoped to a specific application or module, as defined in the `glassfish-resources.xml` for the GlassFish domain.

- To reference the `jndi-name` for an application scoped resource, perform the lookup using the `java:app` prefix.
- To reference the `jndi-name` for a module scoped resource, perform the lookup using the `java:module` prefix.

The `jndi-name` for application-scoped-resources or module-scoped-resources are specified using the format `java:app/jdbc/myDataSource` or `java:module/jdbc/myModuleLevelDataSource`. This naming scope is defined in the Jakarta EE Specification (<https://jakarta.ee/specifications/platform/10/>).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--appname**

Name of the application in which the application scoped resource is defined.

**--modulename**

Name of the module in which the module scoped resource is defined.

## Operands

**pool\_name**

Name of the connection pool to be reinitialized.

Flushing a Connection Pool

This example reinitializes the JDBC connection pool named `--TimerPool`.

```
asadmin> flush-connection-pool --TimerPool
Command flush-connection-pool executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-connector-connection-pools\(1\)](#), [list-jdbc-connection-pools\(1\)](#)

# flush-jmsdest

Purges messages in a JMS destination.

## Synopsis

```
asadmin [asadmin-options] flush-jmsdest [--help]
--desttype {topic|queue}
[--target target]
destname
```

## Description

The **flush-jmsdest** subcommand purges the messages from a physical destination in the server's Java Message Service (JMS) configuration.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --desttype

This option indicates the type of physical destination from which you want to purge messages. The supported destination types are **topic** and **queue**.

#### --target

Purges messages from the physical destination only for the specified target. Valid values are as follows:

#### server

Purges messages from the physical destination for the default server instance. This is the default value.

#### configuration-name

Purges messages from the physical destination in the specified configuration.

**cluster-name**

Purges messages from the physical destination for every server instance in the specified cluster.

**instance-name**

Purges messages from the physical destination for the specified server instance.

## Operands

**dest\_name**

The unique identifier of the JMS destination to be purged.

## Examples

### Example 1 Purging messages from a physical destination

The following subcommand purges messages from the queue named `PhysicalQueue`.

```
asadmin> flush-jmsdest --desttype queue PhysicalQueue
Command flush-jmsdest executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jmsdest\(1\)](#), [list-jmsdest\(1\)](#)

# freeze-transaction-service

Freezes the transaction subsystem

## Synopsis

```
asadmin [asadmin-options] freeze-transaction-service [--help]
[--target target]
```

## Description

The `freeze-transaction-service` subcommand freezes the transaction subsystem, preventing the transaction manager from starting, completing, or changing the state of all in-flight transactions. Invoke this command before rolling back any in-flight transactions. Invoking this subcommand on an already frozen transaction subsystem has no effect. Restarting the server unfreezes the transaction subsystem. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

This option specifies the target on which you are freezing the transaction service. Valid values are:

##### server

Freezes the transaction service for the default server instance `server` and is the default value.

##### configuration\_name

Freezes the transaction service for all server instances that use the named configuration.

##### cluster\_name

Freezes the transaction service for every server instance in the cluster.

##### instance\_name

Freezes the transaction service for a particular server instance.

# Examples

## Example 1 Using freeze-transaction-service

```
% asadmin freeze-transaction-service  
Command freeze-transaction-service executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[recover-transactions\(1\)](#), [rollback-transaction\(1\)](#), [unfreeze-transaction-service\(1\)](#)

[Administering Transactions](#) in Eclipse GlassFish Administration Guide

[Transactions](#) in The Jakarta EE Tutorial

The script content on this page is for navigation purposes only and does not alter the content in any way.

# generate-jvm-report

Shows the JVM machine statistics for a given target instance

## Synopsis

```
generate-jvm-report [--help] [--type=jvm-statistic-type] [--target target]
```

## Description

The `generate-jvm-report` subcommand creates a report that shows the threads (dump of stack trace), classes, memory, or loggers for a given target instance, including the domain administration server (DAS). If a type is not specified, a summary report is generated. This subcommand only provides statistics for the Eclipse GlassFish instance processes. This subcommand provides an alternative to sending Ctrl+Break or `kill -3` signals to Eclipse GlassFish processes to obtain a stack trace for processes that are hanging.

The information in the report is obtained from managed beans (MBeans) and MXBeans that are provided in the Java Platform, Standard Edition (Java SE) or JDK software with which Eclipse GlassFish is being used.

If Eclipse GlassFish is running in the Java Runtime Environment (JRE) software from JDK release 11 or Java SE 11, additional information is provided. For example:

- System load on the available processors
- Object monitors that are currently held or requested by a thread
- Lock objects that a thread is holding, for example, `ReentrantLock` objects and `ReentrantReadWriteLock` objects

If the JRE software cannot provide this information, the report contains the text `NOT_AVAILABLE`.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target for which you are showing JVM machine statistics. Valid values are as follows:

**server**

Specifies the DAS (default).

**instance-name**

Specifies a Eclipse GlassFish instance.

**cluster-name**

Specifies a cluster.

**configuration-name**

Specifies a named configuration.

**--type**

The type of report that is to be generated. Default is **summary**.

**summary**

Displays summary information about the threads, classes, and memory (default).

**memory**

Provides information about heap and non-heap memory consumption, memory pools, and garbage collection statistics for a given target instance.

**class**

Provides information about the class loader for a given target instance.

**thread**

Provides information about threads running and the thread dump (stack trace) for a given target instance.

**log**

Provides information about the loggers that are registered in the Virtual Machine for the Java platform (Java Virtual Machine or JVM machine).<sup>Foot 1</sup>

## Examples

### Example 1 Obtaining Summary Information for the JVM Machine

This example shows a partial listing of a report that is generated if no type is specified. This same report is generated if the **summary** type is specified.

```

asadmin> generate-jvm-report
Operating System Information:
Name of the Operating System: SunOS
Binary Architecture name of the Operating System: sparc, Version: 5.10
Number of processors available on the Operating System: 32
System load on the available processors for the last minute: 7.921875.
(Sum of running and queued runnable entities per minute)
General Java Runtime Environment Information for the VM: 64097@sr1-usca-22
...
sun.desktop = gnome
sun.io.unicode.encoding = UnicodeBig
sun.java.launcher = SUN_STANDARD
sun.jnu.encoding = ISO646-US
sun.management.compiler = HotSpot Client Compiler
sun.os.patch.level = unknown
user.dir = /home/thisuser/GlassFish/glassfish7/glassfish/domains/mydomain4/config
user.home = /home/thisuser
user.language = en
user.name = thisuser
user.timezone = US/Pacific
Command generate-jvm-report executed successfully

```

## Example 2 Obtaining Information for a Particular JVM Machine Type

This example generates a report that shows information on the class loader.

```

asadmin> generate-jvm-report --type=class
Class loading and unloading in the Java Virtual Machine:
Number of classes currently loaded in the Java Virtual Machine: 3,781
Number of classes loaded in the Java Virtual Machine since the startup: 3,868
Number of classes unloaded from the Java Virtual Machine: 87
Just-in-time (JIT) compilation information in the Java Virtual Machine:
Java Virtual Machine compilation monitoring allowed: true
Name of the Just-in-time (JIT) compiler: HotSpot Client Compiler
Total time spent in compilation: 0 Hours 0 Minutes 4 Seconds
Command generate-jvm-report executed successfully.

```

## Exit Status

**0**

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jvm-options\(1\)](#), [delete-jvm-options\(1\)](#), [list-jvm-options\(1\)](#)

---

### Footnote Legend

Footnote 1: The terms "Java Virtual Machine" and "JVM" mean a Virtual Machine for the Java platform.

+

# get

gets the values of configurable or monitorable attributes

## Synopsis

```
asadmin [asadmin-options] get [--help]
[--monitor={true|false}]
[--aggregatedataonly={true|false}]
(dotted-attribute--name)+
```

## Description

The `get` subcommand uses dotted names to get the names and values of configurable or monitorable attributes for Eclipse GlassFish elements.

You can use the [list\(1\)](#) subcommand to display the dotted names that represent individual server components and subsystems. For example, a dotted name might be `server.applications.web-module`. Attributes from the monitoring hierarchy are read-only, but configuration attributes can be modified using the [set\(1\)](#) subcommand. For more detailed information on dotted names, see the [dotted-names\(5ASC\)](#) help page.



Characters that have special meaning to the shell or command interpreter, such as `*` (asterisk), should be quoted or escaped as appropriate to the shell, for example, by enclosing the argument in quotes. In multimode, quotes are needed only for arguments that include spaces, quotes, or backslash.

The following list shows common usage of the `get` subcommand with the `*` (asterisk):

**get \* or get \*.\***

Gets all values on all dotted name prefixes.

**get domain\* or get domain\*.\***

Gets all values on the dotted names that begin with `domain`.

**get \*config\*.\*.\***

Gets all values on the dotted names that match `*config*.*.*`.

**get domain.j2ee-applications.\*.ejb-module.\*.\***

Gets all values on all EJB modules of all applications.

**get \*web-modules.\*.\***

Gets all values on all web modules whether in an application or standalone.

**get \*.\*.\*.\***

Gets all values on all dotted names that have four parts.

# Options

**asadmin-options**

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--monitor****-m**

Defaults to **false**. If set to false, the configurable attribute values are returned. If set to **true**, the monitorable attribute values are returned.

**--aggregatedataonly****-c**

Aggregates monitoring data for all Eclipse GlassFish instances in a cluster. The default value is **false**.

# Operands

**dotted-attribute-name**

Identifies the attribute name in the dotted notation. At least one dotted name attribute is required. The dotted notation is the syntax used to access attributes of configurable entities.

# Examples

## Example 1 Getting the Attributes of a Configurable Element

This example gets the attributes of **listener.http-listener-1**.

```
asadmin> get server.http-service.http-listener.http-listener-1.*
server.http-service.http-listener.http-listener-1.acceptor-threads = 1
server.http-service.http-listener.http-listener-1.address = 0.0.0.0
server.http-service.http-listener.http-listener-1.blocking-enabled = false
server.http-service.http-listener.http-listener-1.default-virtual-server = server
server.http-service.http-listener.http-listener-1.enabled = true
server.http-service.http-listener.http-listener-1.external-port =
server.http-service.http-listener.http-listener-1.family = inet
server.http-service.http-listener.http-listener-1.id = http-listener-1
server.http-service.http-listener.http-listener-1.port = 8080
server.http-service.http-listener.http-listener-1.redirect-port =
server.http-service.http-listener.http-listener-1.security-enabled = false
server.http-service.http-listener.http-listener-1.server-name =
server.http-service.http-listener.http-listener-1.xpowered-by = true
Command get executed successfully.
```

## Example 2 Getting Monitorable Objects

This example gets the configuration attributes for setting the monitoring level and shows whether they are enabled (LOW or HIGH) or disabled (OFF). The **jvm** component is enabled for monitoring.

```
asadmin> get server.monitoring-service.module-monitoring-levels.*
server.monitoring-service.module-monitoring-levels.connector-connection-pool=OFF
server.monitoring-service.module-monitoring-levels.connector-service=OFF
server.monitoring-service.module-monitoring-levels.d-trace=OFF
server.monitoring-service.module-monitoring-levels.ejb-container=OFF
server.monitoring-service.module-monitoring-levels.http-service=OFF
server.monitoring-service.module-monitoring-levels.jdbc-connection-pool=OFF
server.monitoring-service.module-monitoring-levels.jms-service=OFF
server.monitoring-service.module-monitoring-levels.jvm=HIGH
server.monitoring-service.module-monitoring-levels.orb=OFF
server.monitoring-service.module-monitoring-levels.thread-pool=OFF
server.monitoring-service.module-monitoring-levels.transaction-service=OFF
server.monitoring-service.module-monitoring-levels.web-container=OFF
Command get executed successfully.
```

## Example 3 Getting Attributes and Values for a Monitorable Object

This example gets all attributes and values of the **jvm** monitorable object.

```
asadmin> get --monitor server.jvm.*  
server.jvm.HeapSize_Current = 45490176  
server.jvm.HeapSize_Description = Describes JvmHeapSize  
server.jvm.HeapSize_HighWaterMark = 45490176  
server.jvm.HeapSize_LastSampleTime = 1063217002433  
server.jvm.HeapSize_LowWaterMark = 0  
server.jvm.HeapSize_LowerBound = 0  
server.jvm.HeapSize_Name = JvmHeapSize  
server.jvm.HeapSize_StartTime = 1063238840055  
server.jvm.HeapSize_Unit = bytes  
server.jvm.HeapSize_UpperBound = 531628032  
server.jvm.UpTime_Count = 1063238840100  
server.jvm.UpTime_Description = Describes JvmUpTime  
server.jvm.UpTime_LastSampleTime = 1-63238840070  
server.jvm.UpTime_Name = JvmUpTime  
server.jvm.UpTime_StartTime = 1063217002430  
server.jvm.UpTime_Unit = milliseconds  
Command get executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list\(1\), set\(1\)](#)

[dotted-names\(5ASC\)](#)

[Eclipse GlassFish Administration Guide](#)

# get-active-module-config

Displays the current active configuration of a service or instance

## Synopsis

```
asadmin [asadmin-options] get-active-module-config [--help]
[--target target]
[--all={false|true}]
[service_name]
```

## Description

The **get-active-module-config** subcommand displays the current active configuration of a service or instance.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target for which you want to view the current active configuration of a specific service or an entire instance.

Possible values are as follows:

**server**

Displays the current active configuration for the default server instance. This is the default value.

**domain**

Displays the current active configuration for the default domain.

**cluster-name**

Displays the current active configuration for every server instance in the specified cluster.

**instance-name**

Displays the current active configuration for the specified instance.

**--all**

Displays all current active configurations.

The default value is **false**.

## Operands

**service\_name**

The name of the module for which you want to display the current active configuration.

## Examples

### Example 1 Displaying the Current Active Configuration

This example displays the current active configuration for the JMS service in **server-config** (the default configuration).

```
asadmin> get-active-module-config jms-service
At location: domain/configs/config[server-config]
<jms-service default-jms-host="default_JMS_host" type="EMBEDDED"
  <jms-host port="7676" host="localhost" name="default_JMS_host"/>
</jms-service>
Command get-active-module-config executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-module-config\(1\)](#), [delete-module-config\(1\)](#)

# get-client-stubs

Retrieves the application JAR files needed to launch the application client.

## Synopsis

```
asadmin [asadmin-options] get-client-stubs [--help]
--appname application_name
local_directory_path
```

## Description

The `get-client-stubs` subcommand copies the required JAR files for an `AppClient` standalone module or each `AppClient` module in an application from the server machine to the local directory. Each client's generated JAR file is retrieved, along with any required supporting JAR files . The client JAR file name is of the form `app-name`Client.jar``. Before executing the `get-client-stubs` subcommand, you must deploy the application or module. The generated client JAR file is useful for running the application using the `appclient` utility. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --appname

The name of the application or stand-alone client module.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see " [Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

## Operands

### local\_directory\_path

The path to the local directory where the client stub JAR file should be stored.

# Examples

## Example 1 Using get-client-stubs

```
asadmin> get-client-stubs --appname myapplication /sample/example  
Command get-client-stubs executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[deploy\(1\)](#), [redeploy\(1\)](#), [undeploy\(1\)](#)

[appclient\(1M\)](#), [package-appclient\(1M\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# get-health

Provides information on the cluster health

## Synopsis

```
asadmin [asadmin-options] get-health [--help]  
cluster_name
```

## Description

The **get-health** subcommand gets information about the health of the cluster. Note that if the group management service (GMS) is not enabled, the basic information about whether the server instances in this cluster are running or not running is not returned. For each server instance, one of the following states is reported: **not started**, **started**, **stopped**, **rejoined**, or **failed**. This subcommand is available in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### cluster\_name

The name of the cluster for which you want the health information. This subcommand prompts you for the cluster name if you don't specify it.

## Examples

### Example 1 Checking the health of server instances in a cluster

```
asadmin> get-health cluster1
instance1 started since Wed Sep 29 16:32:46 EDT 2010
instance2 started since Wed Sep 29 16:32:45 EDT 2010
Command get-health executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[validate-multicast\(1\)](#)

# import-sync-bundle

Imports the configuration data of a clustered instance or standalone instance from an archive file

## Synopsis

```
asadmin [asadmin-options] import-sync-bundle [--help]
--instance instance-name
[--nodedir node-dir] [--node node-name]
file-name
```

## Description

The **import-sync-bundle** subcommand imports the configuration data of a clustered instance or standalone instance from an archive file that was created by the [export-sync-bundle\(1\)](#) subcommand.

You must run this subcommand on the host where the instance resides. To contact the domain administration server (DAS), this subcommand requires the name of the host where the DAS is running. If a nondefault port is used for administration, this subcommand also requires the port number. You must provide this information through the **--host** option and the **--port** option of the [asadmin\(1M\)](#) utility.

Importing an instance's configuration data transfers the data to a host for an instance without the need for the instance to be able to communicate with the DAS. Importing an instance's configuration data is typically required for the following reasons:

- To reestablish the instance after an upgrade
- To synchronize the instance manually with the domain administration server (DAS) when the instance cannot contact the DAS

The subcommand imports an instance's configuration data by performing the following operations:

- Creating or updating the instance's files and directories
- Attempting to register the instance with the DAS

If the attempt to register the instance with the DAS fails, the subcommand does not fail. Instead, the subcommand displays a warning that the attempt failed. The warning contains the command to run to register the instance with the DAS.

The **import-sync-bundle** subcommand does not contact the DAS to determine the node on which the instance resides. If the node is not specified as an option of the subcommand, the subcommand determines the node from the DAS configuration in the archive file.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --instance

The instance for which configuration data is being imported. The instance must already exist in the DAS configuration. The archive file from which the data is being imported must contain data for the specified instance.

#### --nodedir

The directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is `as-install/nodes`.

#### --node

The node on which the instance resides. If this option is omitted, the subcommand determines the node from the DAS configuration in the archive file.

## Operands

### file-name

The name of the file, including the path, that contains the archive file to import. This operand is required.

## Examples

### Example 1 Importing Configuration Data for a Clustered Instance

This example imports the configuration for the clustered instance `yml12` on the node `sj02` from the archive file `/export/glassfish7/glassfish/domains/domain1-sync/ymlcluster-sync-bundle.zip`.

The command is run on the host `sj02`, which is the host that the node `sj02` represents. The DAS is running on the host `sr04` and uses the default HTTP port for administration.

```
sj02# asadmin --host sr04 import-sync-bundle --node sj02 --instance yml12  
/export/glassfish7/glassfish/domains/domain1/sync/ymlcluster-sync-bundle.zip  
Command import-sync-bundle executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[export-sync-bundle\(1\)](#)

# install-node

Installs Eclipse GlassFish software on specified SSH-enabled hosts

## Synopsis

```
asadmin [asadmin-options] install-node [--help]
[--archive archive]
[--create={false|true}] [--save[={false|true}]]
[--installdir as-install-parent]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile]
[--force={false|true}]
host-list
```

## Description

The **install-node** subcommand installs Eclipse GlassFish software on the hosts that are specified as the operand of the subcommand. This subcommand requires secure shell (SSH) to be configured on the host where the subcommand is run and on each host where the Eclipse GlassFish software is being installed.



This subcommand is equivalent to the [install-node-ssh\(1\)](#) subcommand. To install Eclipse GlassFish software on hosts that use the Distributed Component Object Model (DCOM) remote protocol, use the [install-node-dcom\(1\)](#) subcommand.

If necessary, the subcommand creates a ZIP archive of the Eclipse GlassFish software from the installation where this subcommand is run. The archive does not contain the **domains** directory or the **nodes** directory. These directories are synchronized from the domain administration server (DAS) when instances on nodes that represent the hosts are created and started. The subcommand does not delete the archive after installing the Eclipse GlassFish software from the archive on the specified hosts.

If multiple hosts are specified, the configuration of the following items is the same on all hosts:

- Base installation directory
- SSH port
- SSH user
- SSH key file

If the SSH key file does not exist on a host where the Eclipse GlassFish software is to be installed, the subcommand runs interactively and prompts for a password. To enable the subcommand to run noninteractively, the following conditions must be met:

- The `--interactive` option of the [asadmin\(1M\)](#) utility must be `false`.
- The `--passwordfile` option of the [asadmin](#) utility must specify a password file.
- The password file must contain the `AS_ADMIN_SSHPASSWORD` entry.

The subcommand does not modify the configuration of the DAS.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--archive**

The absolute path to the archive file of the Eclipse GlassFish software that is to be installed. If no archive file is specified, the subcommand creates an archive from the installation of Eclipse GlassFish software from which the subcommand is run. This archive is created in the home directory of the user that is running the command.

**--create**

Specifies whether the subcommand should create an archive file of the Eclipse GlassFish software to install.

**false**

No archive file is created. The subcommand installs the software from the existing archive file that the `--archive` option specifies (default).

**true**

The subcommand creates an archive file from the installation of Eclipse GlassFish software from which the subcommand is run.

**--save**

Specifies whether the archive file from which the software is installed is saved after installation.

**false**

The archive file is not saved. The subcommand deletes the file after installing the software (default).

**true**

The archive file is saved.

**--installdir**

The absolute path to the parent of the base installation directory where the Eclipse GlassFish software is to be installed on each host, for example, `/export/glassfish7/`. If the directory does not exist, the subcommand creates the directory.

The user that is running this subcommand must have write access to the specified directory. Otherwise, an error occurs.

To overwrite an existing an installation of the Eclipse GlassFish software, set the `--force` option to `true`. If the directory already contains an installation and the `--force` option is `false`, an error occurs.

The default is the parent of the base installation directory of the Eclipse GlassFish software on the host where this subcommand is run.

**--sshport**

The port to use for SSH connections to the host where the Eclipse GlassFish software is to be installed. The default is 22.

**--sshuser**

The user on the host where the Eclipse GlassFish software is to be installed that is to run the process for connecting through SSH to the host. The default is the user that is running this subcommand. To ensure that the DAS can read this user's SSH private key file, specify the user that is running the DAS process.

**--sshkeyfile**

The absolute path to the SSH private key file for user that the `--sshuser` option specifies. This file is used for authentication to the `sshd` daemon on the host.

The user that is running this subcommand must be able to reach the path to the key file and read the key file.

The default is a key file in the user's `.ssh` directory. If multiple key files are found, the subcommand uses the following order of preference:

1. `id_rsa`
2. `id_dsa`
3. `identity`

**--force**

Specifies whether the subcommand overwrites an existing installation of the Eclipse GlassFish software in the directory that the `--installdir` option specifies. Possible values are as follows:

**false**

The existing installation is not overwritten (default).

**true**

The existing installation is overwritten.

# Operands

## host-list

A space-separated list of the names of the hosts where the Eclipse GlassFish software is to be installed.

## Examples

### Example 1 Installing Eclipse GlassFish Software at the Default Location

#### Location

This example installs Eclipse GlassFish software on the hosts `sj03.example.com` and `sj04.example.com` at the default location.

```
asadmin> install-node sj03.example.com sj04.example.com
Created installation zip /home/gfuser/glassfish2339538623689073993.zip
Successfully connected to gfuser@sj03.example.com using keyfile /home/gfuser/.ssh/id_rsa
Copying /home/gfuser/glassfish2339538623689073993.zip (81395008 bytes) to sj03.example.com:/export/glassfish7
Installing glassfish2339538623689073993.zip into sj03.example.com:/export/glassfish7
Removing sj03.example.com:/export/glassfish7/glassfish2339538623689073993.zip
Fixing file permissions of all files under sj03.example.com:/export/glassfish7/bin
Successfully connected to gfuser@sj04.example.com using keyfile /home/gfuser/.ssh/id_rsa
Copying /home/gfuser/glassfish2339538623689073993.zip (81395008 bytes) to sj04.example.com:/export/glassfish7
Installing glassfish2339538623689073993.zip into sj04.example.com:/export/glassfish7
Removing sj04.example.com:/export/glassfish7/glassfish2339538623689073993.zip
Fixing file permissions of all files under sj04.example.com:/export/glassfish7/bin
Command install-node executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#)

# install-node-dcom

Installs Eclipse GlassFish software on specified DCOM-enabled hosts

## Synopsis

```
asadmin [asadmin-options] install-node-dcom [--help]
[--archive archive]
[--create={false|true}] [--save[={false|true}]]
[--installdir as-install-parent]
[--windowsuser windows-user] [--windowsdomain windows-domain]
[--force={false|true}]
host-list
```

## Description

The `install-node-dcom` subcommand installs Eclipse GlassFish software on the hosts that are specified as the operand of the subcommand. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol to be configured on the host where the subcommand is run and on each host where the Eclipse GlassFish software is being installed. The DCOM protocol is available only on Windows systems.



To install Eclipse GlassFish software on hosts that use secure shell (SSH), use the [install-node-ssh\(1\)](#) subcommand.

If necessary, the subcommand creates a ZIP archive of the Eclipse GlassFish software from the installation where this subcommand is run. The archive does not contain the `domains` directory or the `nodes` directory. These directories are synchronized from the domain administration server (DAS) when instances on nodes that represent the hosts are created and started. The subcommand does not delete the archive after installing the Eclipse GlassFish software from the archive on the specified hosts.

If multiple hosts are specified, the configuration of the following items is the same on all hosts:

- Base installation directory
- Windows user
- Windows domain

By default, the subcommand runs interactively and prompts for a password to authenticate the Windows user on each host where the Eclipse GlassFish software is being installed. To enable the subcommand to run noninteractively, the following conditions must be met:

- The `--interactive` option of the [asadmin\(1M\)](#) utility must be `false`.
- The `--passwordfile` option of the `asadmin` utility must specify a password file.
- The password file must contain the `AS_ADMIN_WINDOWSPASSWORD` entry.

The subcommand does not modify the configuration of the DAS.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### `--help`

#### `-?`

Displays the help text for the subcommand.

#### `--archive`

The absolute path to the archive file of the Eclipse GlassFish software that is to be installed. If no archive file is specified, the subcommand creates an archive from the installation of Eclipse GlassFish software from which the subcommand is run. This archive is created in the home directory of the user that is running the command.

#### `--create`

Specifies whether the subcommand should create an archive file of the Eclipse GlassFish software to install.

##### `false`

No archive file is created. The subcommand installs the software from the existing archive file that the `--archive` option specifies (default).

##### `true`

The subcommand creates an archive file from the installation of Eclipse GlassFish software from which the subcommand is run.

#### `--save`

Specifies whether the archive file from which the software is installed is saved after installation.

##### `false`

The archive file is not saved. The subcommand deletes the file after installing the software (default).

##### `true`

The archive file is saved.

**--installdir**

The absolute path to the parent of the base installation directory where the Eclipse GlassFish software is to be installed on each host, for example, `C:\glassfish7`. If the directory does not exist, the subcommand creates the directory.

The user that is running this subcommand must have write access to the specified directory. Otherwise, an error occurs.

To overwrite an existing an installation of the Eclipse GlassFish software, set the `--force` option to `true`. If the directory already contains an installation and the `--force` option is `false`, an error occurs.

The default is the parent of the base installation directory of the Eclipse GlassFish software on the host where this subcommand is run.

**--windowsuser****-W**

The user on the host where the Eclipse GlassFish software is to be installed that is to run the process for connecting through DCOM to the host. The default is the user that is running this subcommand.

**--windowsdomain****-d**

The name of the Windows domain that contains the user that the `--windowsuser` option specifies. The default is the name of the host on which the subcommand is run.

**--force**

Specifies whether the subcommand overwrites an existing installation of the Eclipse GlassFish software in the directory that the `--installdir` option specifies. Possible values are as follows:

**false**

The existing installation is not overwritten (default).

**true**

The existing installation is overwritten.

# Operands

**host-list**

A space-separated list of the names of the hosts where the Eclipse GlassFish software is to be installed.

# Examples

## Example 1 Installing Eclipse GlassFish Software at the Default Location

Location

This example installs Eclipse GlassFish software on the hosts `wpmdl1.example.com` and `wpmdl2.example.com` at the default location.

Some lines of output are omitted from this example for readability.

```
asadmin> install-node-dcom wpmdl1.example.com wpmdl2.example.com
Created installation zip C:\glassfish8107276692860773166.zip
Copying 85760199 bytes.....
.....
WROTE FILE TO REMOTE SYSTEM: C:/glassfish7/glassfish_install.zip and
C:/glassfish7/unpack.bat
Output from Windows Unpacker:

C:\Windows\system32>C:

C:\Windows\system32>cd "C:\glassfish7"

C:\glassfish7>jar xvf glassfish_install.zip
 inflated: bin/asadmin
 inflated: bin/asadmin.bat
 inflated: glassfish/bin/appclient
 inflated: glassfish/bin/appclient.bat
 inflated: glassfish/bin/appclient.js
 inflated: glassfish/bin/asadmin
 inflated: glassfish/bin/asadmin.bat
...
 inflated: mq/lib/props/broker/default.properties
 inflated: mq/lib/props/broker/install.properties

Command install-node-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[install-node-ssh\(1\)](#), [uninstall-node-dcom\(1\)](#)

# install-node-ssh

Installs Eclipse GlassFish software on specified SSH-enabled hosts

## Synopsis

```
asadmin [asadmin-options] install-node-ssh [--help]
[--archive archive]
[--create={false|true}] [--save[={false|true}]]
[--installdir as-install-parent]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile]
[--force={false|true}]
host-list
```

## Description

The `install-node-ssh` subcommand installs Eclipse GlassFish software on the hosts that are specified as the operand of the subcommand. This subcommand requires secure shell (SSH) to be configured on the host where the subcommand is run and on each host where the Eclipse GlassFish software is being installed.



This subcommand is equivalent to the `install-node(1)` subcommand. To install Eclipse GlassFish software on hosts that use the Distributed Component Object Model (DCOM) remote protocol, use the `install-node-dcom(1)` subcommand.

If necessary, the subcommand creates a ZIP archive of the Eclipse GlassFish software from the installation where this subcommand is run. The archive does not contain the `domains` directory or the `nodes` directory. These directories are synchronized from the domain administration server (DAS) when instances on nodes that represent the hosts are created and started. The subcommand does not delete the archive after installing the Eclipse GlassFish software from the archive on the specified hosts.

If multiple hosts are specified, the configuration of the following items is the same on all hosts:

- Base installation directory
- SSH port
- SSH user
- SSH key file

If the SSH key file does not exist on a host where the Eclipse GlassFish software is to be installed, the subcommand runs interactively and prompts for a password. To enable the subcommand to run

noninteractively, the following conditions must be met:

- The `--interactive` option of the [asadmin\(1M\)](#) utility must be `false`.
- The `--passwordfile` option of the [asadmin](#) utility must specify a password file.
- The password file must contain the `AS_ADMIN_SSHPASSWORD` entry.

The subcommand does not modify the configuration of the DAS.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### `--help`

`-?`

Displays the help text for the subcommand.

#### `--archive`

The absolute path to the archive file of the Eclipse GlassFish software that is to be installed. If no archive file is specified, the subcommand creates an archive from the installation of Eclipse GlassFish software from which the subcommand is run. This archive is created in the home directory of the user that is running the command.

#### `--create`

Specifies whether the subcommand should create an archive file of the Eclipse GlassFish software to install.

##### `false`

No archive file is created. The subcommand installs the software from the existing archive file that the `--archive` option specifies (default).

##### `true`

The subcommand creates an archive file from the installation of Eclipse GlassFish software from which the subcommand is run.

#### `--save`

Specifies whether the archive file from which the software is installed is saved after installation.

##### `false`

The archive file is not saved. The subcommand deletes the file after installing the software (default).

**true**

The archive file is saved.

**--installdir**

The absolute path to the parent of the base installation directory where the Eclipse GlassFish software is to be installed on each host, for example, `/export/glassfish7/`. If the directory does not exist, the subcommand creates the directory.

The user that is running this subcommand must have write access to the specified directory. Otherwise, an error occurs.

To overwrite an existing an installation of the Eclipse GlassFish software, set the `--force` option to `true`. If the directory already contains an installation and the `--force` option is `false`, an error occurs.

The default is the parent of the base installation directory of the Eclipse GlassFish software on the host where this subcommand is run.

**--sshport**

The port to use for SSH connections to the host where the Eclipse GlassFish software is to be installed. The default is 22.

**--sshuser**

The user on the host where the Eclipse GlassFish software is to be installed that is to run the process for connecting through SSH to the host. The default is the user that is running this subcommand. To ensure that the DAS can read this user's SSH private key file, specify the user that is running the DAS process.

**--sshkeyfile**

The absolute path to the SSH private key file for user that the `--sshuser` option specifies. This file is used for authentication to the `sshd` daemon on the host.

The user that is running this subcommand must be able to reach the path to the key file and read the key file.

The default is a key file in the user's `.ssh` directory. If multiple key files are found, the subcommand uses the following order of preference:

1. `id_rsa`
2. `id_dsa`
3. `identity`

**--force**

Specifies whether the subcommand overwrites an existing installation of the Eclipse GlassFish software in the directory that the `--installdir` option specifies. Possible values are as follows:

**false**

The existing installation is not overwritten (default).

**true**

The existing installation is overwritten.

# Operands

**host-list**

A space-separated list of the names of the hosts where the Eclipse GlassFish software is to be installed.

## Examples

### Example 1 Installing Eclipse GlassFish Software at the Default Location

#### Location

This example installs Eclipse GlassFish software on the hosts `sj03.example.com` and `sj04.example.com` at the default location.

```
asadmin> install-node-ssh sj03.example.com sj04.example.com
Created installation zip /home/gfuser/glassfish2339538623689073993.zip
Successfully connected to gfuser@sj03.example.com using keyfile /home/gfuser/.ssh/id_rsa
Copying /home/gfuser/glassfish2339538623689073993.zip (81395008 bytes) to sj03.example.com:/export/glassfish7
Installing glassfish2339538623689073993.zip into sj03.example.com:/export/glassfish7
Removing sj03.example.com:/export/glassfish7/glassfish2339538623689073993.zip
Fixing file permissions of all files under sj03.example.com:/export/glassfish7/bin
Successfully connected to gfuser@sj04.example.com using keyfile /home/gfuser/.ssh/id_rsa
Copying /home/gfuser/glassfish2339538623689073993.zip (81395008 bytes) to sj04.example.com:/export/glassfish7
Installing glassfish2339538623689073993.zip into sj04.example.com:/export/glassfish7
Removing sj04.example.com:/export/glassfish7/glassfish2339538623689073993.zip
Fixing file permissions of all files under sj04.example.com:/export/glassfish7/bin
Command install-node-ssh executed successfully
```

## Exit Status

**0**

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[install-node\(1\)](#), [install-node-dcom\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-ssh\(1\)](#)

# jms-ping

Checks if the JMS service is up and running

## Synopsis

```
asadmin [asadmin-options] jms-ping [--help]
[-- target target]
```

## Description

The **jms-ping** subcommand checks if the Java Message Service (JMS) service (also known as the JMS provider) is up and running. When you start the Eclipse GlassFish, the JMS service starts by default.

The **jms-ping** subcommand pings only the default JMS host within the JMS service. It displays an error message when it is unable to ping a built-in JMS service.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target for which the operation is to be performed. Valid values are as follows:

##### server

Pings the JMS service for the default server instance. This is the default value

##### configuration-name

Pings the JMS service for all clusters using the specified configuration.

##### cluster-name

Pings the JMS service for the specified cluster.

**instance-name**

Pings the JMS service for the specified server instance.

## Examples

### Example 1 Verifying that the JMS service is running

The following subcommand checks to see if the JMS service is running on the default server.

```
asadmin> jms-ping
JMS-ping command executed successfully
Connector resource test_jms_adapter created.
Command jms-ping executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jms-host\(1\)](#), [delete-jms-host\(1\)](#), [list-jms-hosts\(1\)](#)

# list

Lists configurable or monitorable elements

## Synopsis

```
asadmin [asadmin-options] list [--help]
[--monitor={false|true}]
[dotted-parent-attribute-name]
```

## Description

The `list` subcommand lists configurable and monitorable attributes of Eclipse GlassFish.

The output of the `list` subcommand is a list of the dotted names that represent individual server components and subsystems. For example, `server.applications.web-module`. After you know the particular component or subsystem, you can then use the `get` subcommand to access any attributes, and the `set` subcommand to modify configurable attributes.

The following rules apply to dotted names in a `list` subcommand:



Characters that have special meaning to the shell or command interpreter, such as \* (asterisk), should be quoted or escaped as appropriate to the shell, for example, by enclosing the argument in quotes. In multimode, quotes are needed only for arguments that include spaces, quotes, or backslash.

- Any `list` subcommand that has a dotted name that is not followed by a wildcard (\*) lists the current node's immediate children. For example, the following command lists all immediate children belonging to the server node:

```
asadmin> list server
```

- Any `list` subcommand that has a dotted name followed by a wildcard(\*) lists a hierarchical tree of child nodes from the current node. For example, the following command lists all child nodes of applications and their subsequent child nodes, and so on:

```
asadmin> list server.applications.*
```

- Any `list` subcommand that has a dotted name preceded or followed by a wildcard (\*) of the form dotted name or dottedname lists all nodes and their child nodes that match the regular expression created by the provided matching pattern.

For detailed information about dotted names, see the [dotted-names\(5ASC\)](#) help page.

## Options

### **asadmin-options**

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--monitor**

**-m**

Defaults to false. If set to false, the configurable attribute values are returned. If set to true, the monitorable attribute values are returned.

## Operands

### **dotted-parent-element-name**

Configurable or monitorable element name

## Examples

### **Example 1 Listing Dotted Names of Configurable Elements**

This example lists the elements that can be configured.

```
asadmin> list *
applications
configs
configs.config.server-config
configs.config.server-config.admin-service
configs.config.server-config.admin-service.das-config
configs.config.server-config.admin-service.jmx-connector.system
configs.config.server-config.admin-service.property.adminConsoleContextRoot
configs.config.server-config.admin-service.property.adminConsoleDownloadLocation
configs.config.server-config.admin-service.property.ipsRoot
configs.config.server-config.ejb-container
configs.config.server-config.ejb-container.ejb-timer-service
configs.config.server-config.http-service
configs.config.server-config.http-service.access-log
configs.config.server-config.http-service.virtual-server._asadmin
configs.config.server-config.http-service.virtual-server.server
configs.config.server-config.iiop-service
configs.config.server-config.iiop-service.iiop-listener.SSL
configs.config.server-config.iiop-service.iiop-listener.SSL.ssl
configs.config.server-config.iiop-service.iiop-listener.SSL_MUTUALAUTH
configs.config.server-config.iiop-service.iiop-listener.SSL_MUTUALAUTH.ssl
configs.config.server-config.iiop-service.iiop-listener.orb-listener-1
configs.config.server-config.iiop-service.orb
configs.config.server-config.java-config
configs.config.server-config.jms-service
configs.config.server-config.jms-service.jms-host.default_JMS_host
...
property.administrative.domain.name
resources
resources.jdbc-connection-pool.DerbyPool
resources.jdbc-connection-pool.DerbyPool.property.DatabaseName
resources.jdbc-connection-pool.DerbyPool.property.Password
resources.jdbc-connection-pool.DerbyPool.property.PortNumber
resources.jdbc-connection-pool.DerbyPool.property.User
resources.jdbc-connection-pool.DerbyPool.property.connectionAttributes
resources.jdbc-connection-pool.DerbyPool.property.serverName
resources.jdbc-connection-pool.__TimerPool
resources.jdbc-connection-pool.__TimerPool.property.connectionAttributes
resources.jdbc-connection-pool.__TimerPool.property.databaseName
resources.jdbc-resource.jdbc/__TimerPool
resources.jdbc-resource.jdbc/__default
servers
servers.server.server
servers.server.server.resource-ref.jdbc/__TimerPool
servers.server.server.resource-ref.jdbc/__default
system-applications
Command list executed successfully.
```

## Example 2 Listing Attributes of a Configurable Element

This example lists the attributes of the web container.

```
asadmin> list configs.config.server-config.web-container  
configs.config.server-config.web-container  
configs.config.server-config.web-container.session-config  
Command list executed successfully.
```

## Example 3 Listing Dotted Names of Monitorable Objects

This example lists the names of the monitorable objects that are enabled for monitoring.

```
asadmin> list --monitor *  
server.jvm  
server.jvm.class-loading-system  
server.jvm.compilation-system  
server.jvm.garbage-collectors  
server.jvm.garbage-collectors.Copy  
server.jvm.garbage-collectors.MarkSweepCompact  
server.jvm.memory  
server.jvm.operating-system  
server.jvm.runtime  
server.network  
server.network.admin-listener  
server.network.admin-listener.connections  
server.network.admin-listener.file-cache  
server.network.admin-listener.keep-alive  
server.network.admin-listener.thread-pool  
server.network.http-listener-1  
server.network.http-listener-1.connections  
server.network.http-listener-1.file-cache  
server.network.http-listener-1.keep-alive  
server.network.http-listener-1.thread-pool  
server.transaction-service  
Command list executed successfully.
```

## Exit Status

---

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[get\(1\), set\(1\)](#)

[dotted-names\(5ASC\)](#)

[Eclipse GlassFish Administration Guide](#)

# list-admin-objects

Gets all the administered objects

## Synopsis

```
asadmin [asadmin-options] list-admin-objects [--help]
[target]
```

## Description

The **list-admin-objects** subcommand lists all the administered objects.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

The target for which administered objects are to be listed. Valid values are as follows:

**server**

Lists the administered objects on the default server instance. This is the default value.

**configuration-name**

Lists the administered objects in the specified configuration.

**cluster-name**

Lists the administered objects on all server instances in the specified cluster.

**instance-name**

Lists the administered objects on a specified server instance.

# Examples

## Example 1 Listing Administered Objects

This example lists all the administered objects.

```
asadmin> list-admin-objects
jms/samplequeue
jms/anotherqueue
Command list-admin-objects executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-admin-object\(1\)](#), [delete-admin-object\(1\)](#)

# list-application-refs

Lists the existing application references

## Synopsis

```
asadmin [asadmin-options] list-application-refs [--help]
[--long={false|true}] [target]
```

## Description

The `list-application-refs` subcommand lists all application references in a cluster or an unclustered server instance. This effectively lists all the modules deployed on the specified target (for example, J2EE applications, Web modules, and enterprise bean modules).

If multiple versions of a module or application are deployed, this subcommand lists all versions. To list which version is enabled, set the `--long` option to `true`. For more information about module and application versions, see "Module and Application Versions" in Eclipse GlassFish Application Deployment Guide.

The target instance or instances making up the cluster need not be running or available for this subcommand to succeed.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --long

If `true`, displays whether each module or application listed is enabled. The default is `false`.

## Operands

### target

The target for which you are listing the application references. Valid values are

- `server`- Specifies the default server instance as the target. `server` is the name of the default server instance and is the default value.
- `cluster_name`- Specifies a certain cluster as the target.
- `instance_name`- Specifies a certain server instance as the target.

## Examples

### Example 1 Listing Application References

The following example lists the application references for the unclustered server instance `NewServer`.

```
asadmin> list-application-refs NewServer
ClientSessionMDBApp
MEjbApp
__ejb_container_timer_app
Command list-application-refs executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-application-ref\(1\)](#), [delete-application-ref\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# list-applications

Lists deployed applications

## Synopsis

```
asadmin [asadmin-options] list-applications [--help]
[--long={false|true}] [--resources] [--subcomponents]
[--type type] [target]
```

## Description

The `list-applications` subcommand lists deployed Jakarta EE applications and the type of each application that is listed.

If the `--type` option is not specified, all applications are listed. If the type option is specified, you must specify a type. The possible types are listed in the Options section of this help page.

If multiple versions of a module or application are deployed, this subcommand lists all versions. To list which version is enabled, set the `--long` option to `true`. For more information about module and application versions, see "Module and Application Versions" in Eclipse GlassFish Application Deployment Guide.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --long

If `true`, displays whether each module or application listed is enabled. The default is `false`.

#### --resources

Lists the application-scoped resources for each application. If the `--subcomponents` option is also used, lists the application-scoped resources for each component within the application.

### --subcomponents

Lists the subcomponents of each application. The subcomponents listed depend on the application type. For example, for a Jakarta EE application (EAR file), modules are listed. For a web application, servlets and JSP pages are listed. For an EJB module, EJB subcomponents are listed.

### --type

Specifies the type of the applications that are to be listed. The options are as follows:

- `application`
- `appclient`
- `connector`
- `ejb`
- `web`
- `webservice`

If no type is specified, all applications are listed.

## Operands

### --target

This is the name of the target upon which the subcommand operates. The valid values are as follows:

#### `server`

Lists the applications for the default server instance `server` and is the default value.

#### `domain`

Lists the applications for the domain.

#### `cluster_name`

Lists the applications for the cluster.

#### `instance_name`

Lists the applications for a particular stand-alone server instance.

## Examples

### Example 1 Listing the Web Applications

```
asadmin> list-applications --type web  
hellojsp <web>  
Command list-applications executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-components\(1\)](#), [list-sub-components\(1\)](#), [show-component-status\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# list-audit-modules

Gets all audit modules and displays them

## Synopsis

```
asadmin [asadmin-options] list-audit-modules [--help]
[target]
```

## Description

The **list-audit-modules** subcommand lists all the audit modules. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Specifies the target on which you are listing the audit modules. Valid values are as follows:

**server**

Lists the audit modules for the default server instance **server** and is the default value.

### configuration\_name

Lists the audit modules for the named configuration.

### cluster\_name

Lists the audit modules for every server instance in the cluster.

### instance\_name

Lists the audit modules for a particular server instance.

# Examples

## Example 1 Listing Audit Modules

```
asadmin> list-audit-modules
sampleAuditModule1
sampleAuditModule2
Command list-audit-modules executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-audit-module\(1\)](#), [delete-audit-module\(1\)](#)

# list-auth-realms

Lists the authentication realms

## Synopsis

```
asadmin [asadmin-options] list-auth-realms [--help]
[target]
```

## Description

The **list-auth-realms** subcommand lists the authentication realms. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

The name of the target for which you want to list the authentication realms.

**server**

Lists the realms for the default server instance **server** and is the default value.

**configuration\_name**

Lists the realms for the named configuration.

**cluster\_name**

Lists the realms for every server instance in the cluster.

**instance\_name**

Lists the realms for a particular server instance.

# Examples

## Example 1 Listing authentication realms

```
asadmin> list-auth-realms
file
ldap
certificate
db
Command list-auth-realms executed successfully
```

Where file, ldap, certificate, and db are the available authentication realms.

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-auth-realm\(1\)](#), [delete-auth-realm\(1\)](#)

# list-backups

Lists all backups

## Synopsis

```
asadmin [asadmin-options] list-backups [--help]
[--long[={false|true}]]
[--domaindir domain-root-dir]
[--backupdir backup-directory]
[--backupconfig backup-config-name]
[domain-name]
```

## Description

The **list-backups** subcommand displays information about domain backups.

This subcommand is supported in local mode only in Eclipse GlassFish, and is support in local mode and remote mode in Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

**-?**

Displays the help text for the subcommand.

#### --long

**-l**

Displays detailed information about each backup.

The default value is **false**.

#### --domaindir

Specifies the domain root directory, the parent directory of the domain upon which the command will operate.

The default value is **as-install/domains**.

#### --backupdir

Specifies the directory under which backup files are stored.

The default value is **as-install/domains/domain-dir/backups**. If the domain is not in the default

location, the location is domain-dir/[backups](#).

#### **--backupconfig**

(Supported only in Eclipse GlassFish.) Restricts the listing of backup files in the backup directory to those for the specified domain backup configuration.

## Operands

### **domain-name**

Specifies the domain for which backups are listed.

This operand is optional if only one domain exists in the Eclipse GlassFish installation.

## Examples

### Example 1 Listing Domain Backups

This example provides detailed information about backups in the default domain.

```
asadmin> list-backups --long
```

```
Description          : domain1 backup created on 2021_12_20 by user dmatej
GlassFish Version   : Eclipse GlassFish 7.0.0 (build 2021-12-10T19:08:14+0100)
Backup User         : admin
Backup Date         : Mon Dec 20 19:24:17 CET 2021
Domain Name        : domain1
Backup Type         : full
Backup Config Name  :
Backup Filename (origin)  :
/glassfish7/glassfish/domains/domain1/backups/domain1_2021_12_20_v00001.zip
Domain Directory    : /glassfish7/glassfish/domains/domain1

Description          : domain1 backup created on 2021_12_20 by user dmatej
GlassFish Version   : Eclipse GlassFish 7.0.0 (build 2021-12-10T19:08:14+0100)
Backup User         : admin
Backup Date         : Mon Dec 20 19:24:20 CET 2021
Domain Name        : domain1
Backup Type         : full
Backup Config Name  :
Backup Filename (origin)  :
/glassfish7/glassfish/domains/domain1/backups/domain1_2021_12_20_v00002.zip
Domain Directory    : /glassfish7/glassfish/domains/domain1
```

Command list-backups executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[backup-domain\(1\)](#), [restore-domain\(1\)](#)

# list-batch-job-executions

Lists batch job executions and execution details

## Synopsis

```
asadmin [asadmin-options] list-batch-job-executions [--help]
[--target target]
[--executionid execution-id]
[--long={false|true}]
[--output output]
[--header={false|true}]
[instance_ID]
```

## Description

The **list-batch-job-executions** subcommand lists batch job executions and execution details.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

Specifies the target for which to list batch job executions and execution details. Valid values are as follows:

**server**

Lists executions for the default server instance **server** and is the default value.

**cluster-name**

Lists executions for every server instance in the cluster.

**instance-name**

Lists executions for a particular server instance.

**--executionid****-x**

Specifies the execution ID of a specific batch job execution.

**--long****-l**

Displays detailed information about batch job executions. The default value is `false`.

**--output****-o**

Displays specific details about batch job executions. Use a comma-separated list to specify the details to display and their order. The values are case-insensitive. A subset of all possible headings is displayed by default.

Possible values are as follows:

**jobname**

Displays the name of the job.

**executionid**

Displays the ID assigned to the execution of the batch job. A new execution is created the first time a job is started and every time the existing execution is restarted.

**starttime**

Displays the start time of the execution.

**endtime**

Displays the finish time of the execution.

**batchstatus**

Displays the status of the execution as set by the batch runtime.

**exitstatus**

Displays the status of the execution as set by the Job XML for the job or by the batch application. By default, the exit status and the batch status are the same unless the exit status is explicitly overridden.

**jobparameters**

Displays the properties passed to the batch runtime for the batch job execution, listed as name/value pairs.

**stepcount**

Displays the number of steps in the batch job execution.

**--header****-h**

Specifies whether column headings are displayed when the **--long** option is used. The default value is **true**. To suppress the headings, set the **--header** option to **false**.

## Operands

**instance\_id**

The ID of the job instance for which to list execution details.

## Examples

### Example 1 Listing Batch Job Executions

This example lists batch job executions for the default server instance and displays specific details.

```
asadmin> list-batch-job-executions -o=jobname,executionid,batchstatus,exitstatus
JOBNAME  EXECUTIONID  BATCHSTATUS  EXITSTATUS
payroll   9           COMPLETED    COMPLETED
bonus     6           FAILED       FAILED
Command list-batch-job-executions executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-batch-jobs\(1\)](#), [list-batch-job-steps\(1\)](#), [list-batch-runtime-configuration\(1\)](#), [set-batch-runtime-configuration\(1\)](#)

# list-batch-jobs

Lists batch jobs

## Synopsis

```
asadmin [asadmin-options] list-batch-jobs [--help]
[--target target]
[--long={false|true}]
[--output output]
[--header={false|true}]
[job_name]
```

## Description

The **list-batch-jobs** subcommand lists batch jobs and job details.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target for which to list batch jobs and job details. Valid values are as follows:

##### server

Lists batch jobs for the default server instance **server** and is the default value.

##### cluster-name

Lists batch jobs for every server instance in the cluster.

##### instance-name

Lists batch jobs for a particular server instance.

#### --long

-l

Displays detailed information about batch jobs. The default value is **false**.

**--output****-o**

Displays specific details about batch jobs. Use a comma-separated list to specify the details to display and their order. The values are case-insensitive. The **jobname** and **instancecount** column headings are displayed by default.

Possible values are as follows:

**jobname**

Displays the name of the job.

**appname**

Displays the name of the application.

**instancecount**

Displays the number of job instances.

**instanceid**

Displays the ID assigned to the job instance.

**executionid**

Displays the ID assigned to the execution of the batch job. A new execution is created the first time a job is started and every time the existing execution is restarted.

**batchstatus**

Displays the status of the job as set by the batch runtime.

**starttime**

Displays the start time of the job.

**endtime**

Displays the finish time of the job.

**exitstatus**

Displays the status of the job as set by the Job XML for the job or by the batch application. By default, the exit status and the batch status are the same unless the exit status is explicitly overridden.

**--header****-h**

Specifies whether column headings are displayed when the **--long** option is used. The default value is **true**. To suppress the headings, set the **--header** option to **false**.

# Operands

## job\_name

The name of the job for which to list details.

# Examples

## Example 1 Listing Batch Jobs

This example lists batch jobs for the default server instance.

```
asadmin> list-batch-jobs
JOBNAME INSTANCECOUNT
payroll    9
bonus      6
Command list-batch-jobs executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[list-batch-job-executions\(1\)](#), [list-batch-job-steps\(1\)](#), [list-batch-runtime-configuration\(1\)](#), [set-batch-runtime-configuration\(1\)](#)

# list-batch-job-steps

Lists steps for a specific batch job execution

## Synopsis

```
asadmin [asadmin-options] list-batch-job-steps [--help]
[--long={false|true}]
[--target target]
[--output output]
[--header={false|true}]
execution_id
```

## Description

The **list-batch-job-steps** subcommand lists steps for a specific batch job execution.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target for which to list batch job steps. Valid values are as follows:

##### server

Lists steps for the default server instance **server** and is the default value.

##### cluster-name

Lists steps for every server instance in the cluster.

##### instance-name

Lists steps for a particular server instance.

#### --long

-l

Displays detailed information about batch job steps. The default value is **false**.

**--output****-o**

Displays specific details about batch job steps. Use a comma-separated list to specify the details to display and their order. The values are case-insensitive. A subset of all possible headings is displayed by default. Possible values are as follows:

**stepname**

Displays the name of the step.

**stepid**

Displays the step ID.

**starttime**

Displays the start time of the step.

**endtime**

Displays the finish time of the step.

**batchstatus**

Displays the status of the step as set by the batch runtime.

**exitstatus**

Displays the status of the step as set by the Job XML for the job or by the batch application. By default, the exit status and the batch status are the same unless the exit status is explicitly overridden.

**stepmetrics**

Displays metrics for the step.

**value**

Displays a value for each step metric. The value represents the number of items read, written, committed, and so on.

**--header****-h**

Specifies whether column headings are displayed when the **--long** option is used. The default value is **true**. To suppress the headings, set the **--header** option to **false**.

# Operands

**execution\_id**

The ID of the execution for which to list batch job steps and details.

# Examples

## Example 1 Listing Batch Job Steps

This example lists batch job steps and specific step details for a job execution with the execution ID of 7. The target is the default server instance.

Some lines of output are omitted from this example for readability.

```
asadmin> list-batch-job-steps o=stepname,stepid,batchstatus,stepmetrics 7
STEPNAME    STEPID    BATCHSTATUS    STEPMETRICS
prepare      7         COMPLETED      METRICNAME      VALUE
                           READ_COUNT     8
                           WRITE_COUNT    8
                           PROCESS_SKIP_COUNT 0
process      8         COMPLETED      METRICNAME      VALUE
                           READ_COUNT     8
                           WRITE_COUNT    8
                           PROCESS_SKIP_COUNT 0
...
Command list-batch-job-steps executed successfully.
```

## Exit Status

0

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-batch-jobs\(1\)](#), [list-batch-job-executions\(1\)](#), [list-batch-runtime-configuration\(1\)](#), [set-batch-runtime-configuration\(1\)](#)

# list-batch-runtime-configuration

Displays the configuration of the batch runtime

## Synopsis

```
asadmin [asadmin-options] list-batch-runtime-configuration [--help]
[--target target]
[--output output]
[--header={false|true}]
```

## Description

The **list-batch-runtime-configuration** subcommand displays the configuration of the batch runtime. Batch runtime configuration data is stored in the **config** element in **domain.xml**.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

**-?**

Displays the help text for the subcommand.

#### --target

Specifies the target for which to list the batch runtime configuration. Valid values are as follows:

##### server

Lists the batch runtime configuration for the default server instance **server** and is the default value.

##### cluster-name

Lists the batch runtime configuration for every server instance in the cluster.

##### instance-name

Lists the batch runtime configuration for a particular server instance.

#### --output

**-o**

Displays specific details about the batch runtime configuration. Use a comma-separated list to specify the details to display and their order. The values are case-insensitive. The

`datasourcelookupname` and `executorservicelookupname` column headings are displayed by default.

Possible values are as follows:

#### `datasourcelookupname`

The JNDI lookup name of the data source used to store job information. By default, the batch runtime uses the default data source `jdbc/_TimerPool`.

#### `executorservicelookupname`

The JNDI lookup name of the managed executor service used to provide threads to jobs. By default, the batch runtime uses the default managed executor service `concurrent/_defaultManagedExecutorService`.

`--header`

`-h`

Specifies whether column headings are displayed when the `--long` option is used. The default value is `true`. To suppress the headings, set the `--header` option to `false`.

## Examples

### Example 1 Listing Batch Runtime Configuration

The following example lists the configuration of the batch runtime for the default server instance.

```
asadmin> list-batch-runtime-configuration
DATASOURCELOOKUPNAME      EXECUTORSERVICELOOKUPNAME
jdbc/_default              concurrent/_defaultManagedExecutorService
Command list-batch-runtime-configuration executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[set-batch-runtime-configuration\(1\)](#), [list-batch-jobs\(1\)](#), [list-batch-job-executions\(1\)](#), [list-batch-job-](#)

---

**steps(1)**

# list-clusters

Lists existing clusters in a domain

## Synopsis

```
asadmin [asadmin-options] list-clusters [--help]
[target]
```

## Description

The **list-clusters** subcommand lists existing clusters in a domain. The list can be filtered by cluster, instance, node, or configuration. For each cluster that is listed, the subcommand indicates whether the cluster is running.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

## Operands

### target

Filters the list of clusters by specifying the target for which the clusters are to be listed. Valid values are as follows:

#### domain

Lists all clusters in the domain (default).

#### cluster-name

Lists only the specified cluster.

#### instance-name

Lists the cluster of which the specified instance is a member.

**node-name**

Lists the clusters that contain an instance that resides on the specified node. For example, if instance `pmdi1` in cluster `pmdc` and instance `yml1` in cluster `ymlc` reside on node `n1`, `pmdc` and `ymlc` are listed.

**configuration-name**

Lists all clusters that contain instances whose configuration is defined by the named configuration.

## Examples

### Example 1 Listing All Clusters in a Domain

This example lists all clusters in the current domain.

```
asadmin> list-clusters
pmdclust not running
ymlclust not running

Command list-clusters executed successfully.
```

### Example 2 Displaying the Status of a Cluster

This example displays status of the cluster `ymlclust`, which is not running.

```
asadmin> list-clusters ymlclust
ymlclust not running

Command list-clusters executed successfully.
```

### Example 3 Listing All Clusters That Are Associated With a Node

This example lists the clusters that contain an instance that resides on the node `sj02`.

```
asadmin> list-clusters sj02  
ymlclust not running
```

Command list-clusters executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-cluster\(1\)](#), [delete-cluster\(1\)](#), [start-cluster\(1\)](#), [stop-cluster\(1\)](#)

# list-commands

Lists available commands

## Synopsis

```
asadmin [asadmin-options] list-commands [--help]
[--localonly={false|true}] [--remoteonly={false|true}]
pattern-list
```

## Description

The **list-commands** subcommand lists the **asadmin** subcommands.

By default, the **list-commands** subcommand displays a list of local subcommands followed by a list of remote subcommands. You can specify that only remote subcommands or only local subcommands are listed and that only subcommands whose names contain a specified text string are listed.

This subcommand is supported in local mode and remote mode.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --localonly

If this option is set to true, only local commands are listed. Default is false.

If this option is set to true, the **--remoteonly** option must be set to false. Otherwise, an error occurs.

#### --remoteonly

If this option is set to true, only remote commands are listed. Default is false.

If this option is set to true, the **--localonly** option must be set to false. Otherwise, an error occurs.

## Operands

## pattern-list

A space-separated list of text strings on which to filter the list of subcommands. Only the subcommands that contain any one of the specified text strings is listed.

# Examples

## Example 1 Listing the Local Subcommands

This example lists only the local subcommands.

```
asadmin> list-commands --localonly=true
***** Local Commands *****
change-admin-password
change-master-password
create-domain
create-service
delete-domain
export
help
list-commands
list-domains
login
monitor
multimode
restart-domain
start-database
start-domain
stop-database
stop-domain
unset
verify-domain-xml
version
Command list-commands executed successfully.
```

## Example 2 Filtering the Subcommands That Are Listed

This example lists only the subcommands whose names contain the text `configure` or `set`.

```
asadmin> list-commands configure set
***** Local Commands *****
setup-ssh
unset

***** Remote Commands *****
configure-jms-cluster          set-log-levels
configure-lb-weight             set-web-context-param
configure-ldap-for-admin       set-web-env-entry
set                           unset-web-context-param
set-log-attributes            unset-web-env-entry
```

Command list-commands executed successfully.

### Example 3 Listing All Subcommands

This example first displays a list of the local subcommands, followed by a partial list of the remote subcommands.

```
asadmin> list-commands
***** Local Commands *****
change-admin-password
change-master-password
create-domain
create-service
delete-domain
export
help
list-commands
list-domains
login
monitor
multimode
restart-domain
start-database
start-domain
stop-database
stop-domain
unset
verify-domain-xml
version

***** Remote Commands *****
__locations           enable
```

add-resources	enable-monitoring
configure-ldap-for-admin	flush-jmsdest
create-admin-object	freeze-transaction-service
create-audit-module	generate-jvm-report
create-auth-realm	get
create-connector-connection-pool	get-client-stubs
create-connector-resource	get-host-and-port
create-connector-security-map	jms-ping
create-connector-work-security-map	list
create-custom-resource	list-admin-objects
create-file-user	list-app-refs
create-http	list-applications
create-http-listener	list-audit-modules
create-iiop-listener	list-auth-realms
create-javamail-resource	list-components
create-jdbc-connection-pool	list-connector-connection-pools
create-jdbc-resource	list-connector-resources
create-jms-host	list-connector-security-maps
create-jms-resource	list-connector-work-security-maps
create-jmsdest	list-containers
create-jndi-resource	list-custom-resources
create-jvm-options	list-file-groups
create-lifecycle-module	list-file-users
create-message-security-provider	list-http-listeners
create-network-listener	list-iiop-listeners
create-passwordAlias	list-javamail-resources
create-profiler	list-jdbc-connection-pools
create-protocol	list-jdbc-resources
create-resource-adapter-config	list-jms-hosts
create-resource-ref	list-jms-resources
create-ssl	list-jmsdest
create-system-properties	list-jndi-entries
create-threadpool	list-jndi-resources
create-transport	list-jvm-options
create-virtual-server	list-lifecycle-modules
delete-admin-object	list-logger-levels
delete-audit-module	list-message-security-providers
...	

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[list-components\(1\)](#), [list-containers\(1\)](#), [list-modules\(1\)](#)

# list-components

Lists deployed components

## Synopsis

```
asadmin [asadmin-options] list-components [--help]
[--long={false|true}] [--resources] [--subcomponents]
[--type type] [target]
```

## Description



The `list-components` subcommand is deprecated. Use the `list-applications` subcommand instead.

The `list-components` subcommand lists all deployed Jakarta EE components.

If the `--type` option is not specified, all components are listed. If the type option is specified, you must specify a type. The possible types are listed in the Options section in this help page.

If multiple versions of a module or application are deployed, this subcommand lists all versions. To list which version is enabled, set the `--long` option to `true`. For more information about module and application versions, see "Module and Application Versions" in Eclipse GlassFish Application Deployment Guide.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --long

If `true`, displays whether each module or application listed is enabled. The default is `false`.

#### --resources

Lists the application-scoped resources for each component. If the `--subcomponents` option is also used, lists the application-scoped resources for each component within an application.

**--subcomponents**

Lists the subcomponents of each component. The subcomponents listed depend on the component type. For example, for a Jakarta EE application (EAR file), modules are listed. For a web application, servlets and JSP pages are listed. For an EJB module, EJB subcomponents are listed.

**--type**

Specifies the type of the components that are to be listed. The options are as follows:

- **application**
- **appclient**
- **connector**
- **ejb**
- **web**
- **webservice**

If no type is specified, all components are listed.

## Operands

**target**

This is the name of the target upon which the subcommand operates. The valid values are:

**server**

Lists the components for the default server instance **server** and is the default value.

**domain**

Lists the components for the domain.

**cluster\_name**

Lists the components for the cluster.

**instance\_name**

Lists the components for a particular stand-alone server instance.

## Examples

### Example 1 Listing Components

This example lists the connector components. (**cciblackbox-tx.rar** was deployed.)

```
asadmin> list-components --type connector  
cciblackbox-tx <connector>  
Command list-components executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [show-component-status\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# list-configs

Lists named configurations

## Synopsis

```
asadmin [asadmin-options] list-configs [--help]
[target]
```

## Description

The **list-configs** subcommand lists named configurations in the configuration of the domain administration server (DAS). The list can be filtered by cluster, instance, or named configuration.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

## Operands

### target

Filters the list of configurations. Valid values are as follows:

#### domain

Lists all named configurations in the current domain.

#### cluster-name

Lists the named configuration that defines the configuration of instances in the specified cluster.

#### instance-name

Lists the named configuration that defines the configuration of the specified instance.

#### configuration-name

Lists the specified named configuration. Use this option to determine whether a named

configuration exists.

## Examples

### Example 1 Listing All Named Configurations in a Domain

This example lists all named configurations in the current domain.

```
asadmin> list-configs
server-config
default-config
pmdclust-config
pmdsharedconfig
pmddcpinst-config
ymlclust-config
il1-config
il2-config
```

Command list-configs executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[copy-config\(1\)](#), [delete-config\(1\)](#)

[configuration\(5ASC\)](#)

# list-connector-connection-pools

Lists the existing connector connection pools

## Synopsis

```
asadmin [asadmin-options] list-connector-connection-pools [--help]
```

## Description

The `list-connector-connection-pools` subcommand lists connector connection pools that have been created.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Examples

### Example 1 Listing the Connector Connection Pools

This example lists the existing connector connection pools.

```
asadmin> list-connector-connection-pools
jms/qConnPool
Command list-connector-connection-pools executed successfully
```

## Exit Status

`0`

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-connection-pool\(1\)](#), [delete-connector-connection-pool\(1\)](#), [ping-connection-pool\(1\)](#)

# list-connector-resources

Lists all connector resources

## Synopsis

```
asadmin [asadmin-options] list-connector-resources [--help]
[target]
```

## Description

The `list-connector-resources` subcommand lists all connector resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### target

The target for which the connector resources are to be listed. Valid values are as follows:

`server`

Lists the connector resources on the default server instance. This is the default value.

`domain`

Lists the connector resources for the domain.

`cluster-name`

Lists the connector resources on all server instances in the specified cluster.

`instance-name`

Lists the connector resources on a specified server instance.

# Examples

## Example 1 Listing Connector Resources

This example lists all existing connector resources.

```
asadmin> list-connector-resources  
jms/qConnFactory  
Command list-connector-resources executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-resource\(1\)](#), [delete-connector-resource\(1\)](#)

# list-connector-security-maps

Lists the security maps belonging to the specified connector connection pool

## Synopsis

```
asadmin [asadmin-options] list-connector-security-maps [--help]
[--securitymap securitymap]
[--verbose={false|true}] [--target target]
pool-name
```

## Description

The `list-connector-security-maps` subcommand lists the security maps belonging to the specified connector connection pool.

For this subcommand to succeed, you must have first created a connector connection pool using the `create-connector-connection-pool` subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --securitymap

Specifies the name of the security map contained within the connector connection pool from which the identity and principals should be listed. With this option, `--verbose` is redundant.

#### --verbose

If set to `true`, returns a list including the identity, principals, and security name. The default is `false`.

#### --target

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

# Operands

## pool-name

Name of the connector connection pool for which you want to list security maps.

# Examples

## Example 1 Listing the Connector Security Maps

This example lists the existing connector security maps for the pool named `connector-Pool1`.

```
asadmin> list-connector-security-maps connector-Pool1
securityMap1
Command list-connector-security-maps executed successfully.
```

# Exit Status

0

subcommand executed successfully

1

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[create-connector-security-map\(1\)](#), [delete-connector-security-map\(1\)](#), [update-connector-security-map\(1\)](#)

# list-connector-work-security-maps

Lists the work security maps belonging to the specified resource adapter

## Synopsis

```
asadmin [asadmin-options] list-connector-work-security-maps [--help]
[--securitymap securitymap]
resource_adapter_name
```

## Description

The `list-connector-work-security-maps` subcommand lists the work security maps belonging to the specified resource adapter.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

### `--securitymap`

Specifies the name of the security map contained within the resource adapter from which the identity and principals should be listed.

## Operands

### `resource_adapter_name`

The name of the resource adapter for which you want to list security maps.

## Examples

## Example 1 Listing Connector Work Security Maps

This example lists the current connector work security maps for the resource adapter named `my_resource_adapter`.

```
asadmin> list-connector-work-security-maps my_resource_adapter
workSecurityMap1: EIS principal=eis-principal-2, mapped principal=server-principal-2
workSecurityMap1: EIS principal=eis-principal-1, mapped principal=server-principal-1
workSecurityMap2: EIS principal=eis-principal-2, mapped principal=server-principal-2
workSecurityMap2: EIS principal=eis-principal-1, mapped principal=server-principal-1
Command list-connector-work-security-maps executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-work-security-map\(1\)](#), [delete-connector-work-security-map\(1\)](#), [update-connector-work-security-map\(1\)](#)

# list-containers

Lists application containers

## Synopsis

```
asadmin [asadmin-options] list-containers [--help]
```

## Description

The **list-containers** subcommand displays a list of application containers.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Examples

### Example 1 Listing the Application Containers

This example lists the current application containers.

```
asadmin> list-containers
List all known application containers
Container : grizzly
Container : ejb
Container : webservices
Container : ear
Container : appclient
Container : connector
Container : jpa
Container : web
Container : osgi
Container : security
Container : webbeans
```

Command list-containers executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-commands\(1\)](#), [list-components\(1\)](#), [list-modules\(1\)](#)

# list-context-services

Lists context service resources

## Synopsis

```
asadmin [asadmin-options] list-context-services [--help]
[target]
```

## Description

The **list-context-services** subcommand lists context service resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Specifies the target for which context service resources are to be listed. Valid targets are:

**server**

Lists the resources on the default server instance. This is the default value.

**domain**

Lists the resources for the domain.

**cluster-name**

Lists the resources on all server instances in the specified cluster.

**instance-name**

Lists the resources on a specified server instance.

# Examples

## Example 1 Listing Context Service Resources

This example lists context service resources on the default server instance.

```
asadmin> list-context-services
concurrent/_defaultContextService
concurrent/myContextService1
concurrent/myContextService2
Command list-context-services executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-context-service\(1\)](#), [delete-context-service\(1\)](#)

# list-custom-resources

Gets all custom resources

## Synopsis

```
asadmin [asadmin-options] list-custom-resources [--help]
[target]
```

## Description

The **list-custom-resources** subcommand lists the custom resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

This operand specifies the location of the custom resources. Valid targets are:

**server**

Lists the resources on the default server instance. This is the default value

**domain**

Lists the resources in the domain.

**cluster\_name**

Lists the resources for every server instance in the cluster.

**instance\_name**

Lists the resources for a particular server instance.

# Examples

## Example 1 Listing Custom Resources

This example lists the current custom resources.

```
asadmin> list-custom-resources
sample_custom_resource01
sample_custom_resource02
Command list-custom-resources executed successfully.
```

## Example 2 Using the list-custom-resources command with a target

The following example displays the usage of this command.

```
asadmin> list-custom-resources --user admin --passwordfile
passwords.txt --host plum --port 4848 target6

sample_custom_resource03
sample_custom_resource04
Command list-custom-resources executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-custom-resource\(1\)](#),[delete-custom-resource\(1\)](#)

# list-domains

Lists the domains in the specified directory

## Synopsis

```
asadmin [asadmin-options] list-domains [--help]
[--domaindir domaindir]
[--long={false|true}]
[--header={false|true}]
```

## Description

The **list-domains** subcommand lists the domains in the specified domains directory. If the domains directory is not specified, the domains in the default directory are listed. If there is more than one domains directory, the **--domaindir** option must be specified. The status of each domain is included.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --domaindir

The directory where the domains are to be listed. If specified, the path must be accessible in the files stem. If not specified, the domains in the domain root directory are listed. The default location of the domain root directory is `as-install/domains`.

#### --long

#### -l

Displays detailed information about the administration servers in the listed domains, including host names and port numbers. The default value is `false`.

#### --header

#### -h

Specifies whether a header is displayed when the **--long** option is used. The default value is `true`. To

suppress the header, set the `--header` option to `false`.

## Examples

### Example 1 Listing Domains

This example lists the domains in the default directory.

```
asadmin> list-domains
Name: domain1 Status: Running
Name: domain2 Status: Not running
Name: domain4 Status: Running, restart required to apply configuration changes
Command list-domains executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-domain\(1\)](#), [delete-domain\(1\)](#), [start-domain\(1\)](#), [stop-domain\(1\)](#),

# list-file-groups

Lists file groups

## Synopsis

```
asadmin [asadmin-options] list-file-groups [--help]
[--name username] [--authrealmname auth_realm_name]
[--target target]
```

## Description

The **list-file-groups** subcommand lists the file users and groups supported by the file realm authentication. This subcommand lists available groups in the file user. If the **--name** option is not specified, all groups are listed.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--name**

Identifies the name of the file user for whom the groups will be listed.

**--authrealmname**

The name of the authentication realm for which to list available groups.

**--target**

This option specifies which configurations you can list. Valid targets are:

**server**

Lists the file groups in the current server. This is the default value.

**cluster\_name**

Lists the file groups in a cluster.

**instance\_name**

Lists the file groups for a particular instance.

## Examples

### Example 1 Listing Groups in all File Realms

This example list all file realm groups defined for the server.

```
asadmin> list-file-groups
staff
manager
Command list-file-groups executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-file-user\(1\)](#), [delete-file-user\(1\)](#), [list-file-users\(1\)](#), [update-file-user\(1\)](#)

# list-file-users

Lists the file users

## Synopsis

```
asadmin [asadmin-options] list-file-users [--help]
[--authrealmname auth_realm_name] [target]
```

## Description

The **list-file-users** subcommand displays a list of file users supported by file realm authentication.

## Options

**--help**

**-?**

Displays the help text for the subcommand.

**--authrealmname**

Lists only the users in the specified authentication realm.

## Operands

**target**

Specifies the target for which you want to list file users. The following values are valid:

**server**

Lists the file users on the default server instance. This is the default value.

**configuration\_name**

Lists the file users in the specified configuration.

**cluster\_name**

Lists the file users on all server instances in the specified cluster.

**instance\_name**

Lists the file users on a specified server instance.

# Examples

## Example 1 Listing Users in a Specific File Realm

The following example lists the users in the file realm named `sample_file_realm`.

```
asadmin> list-file-users --authrealmname sample_file_realm
sample_user05
sample_user08
sample_user12
Command list-file-users executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-file-user\(1\)](#), [delete-file-user\(1\)](#), [list-file-groups\(1\)](#), [update-file-user\(1\)](#)

# list-http-lb-configs

Lists load balancer configurations

## Synopsis

```
asadmin [asadmin-options] list-http-lb-configs [--help]
[target]
```

## Description

The **list-http-lb-configs** subcommand lists the load balancer configurations. List them all or list them by the cluster or server instance they reference.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Lists the load balancers by target. Valid values are:

- **cluster\_name**- The name of a target cluster.
- **instance\_name**- The name of a target server instance.

## Examples

## Example 1 Listing Load Balancer Configurations Without a Target

This example lists all load balancer configurations defined for all Eclipse GlassFish clusters and instances.

```
asadmin> list-http-lb-configs  
  
mycluster-http-lb-config  
serverinstlb  
Command list-http-lb-configs executed successfully.
```

## Example 2 Listing Load Balancer Configurations for a Specific Target

This example lists the load balancer configuration defined for a cluster named `mycluster`.

```
asadmin> list-http-lb-configs mycluster  
  
mycluster-http-lb-config  
Command list-http-lb-configs executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb-config\(1\)](#), [delete-http-lb-config\(1\)](#)

# list-http-lbs

Lists load balancers

## Synopsis

```
asadmin [asadmin-options] list-http-lbs [--help]
[--long={false|true}]
[--output output]
[--header={false|true}]
[name]
```

## Description

Use the **list-http-lbs** subcommand to list physical load balancers.



This subcommand is only applicable to Eclipse GlassFish. This subcommand is not applicable to Eclipse GlassFish.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--long**

**-l**

Displays detailed information about each load balancer. The default value is **false**.

**--output**

**-o**

Displays specific details about each load balancer. Use a comma-separated list to specify the details you want to display and their order. For example, **list-http-lbs --output name,device-host,device-port**. The values are case-insensitive.

Possible values are as follows:

**device-host**

Displays the device host or the IP address of the load balancing device. This host or IP is where

the physical load balancer resides.

**name**

Displays the name of the load balancer.

**auto-apply-enabled**

Displays whether the Auto Apply feature is enabled.

**lb-config-name**

Displays the name of the load balancer configuration.

**device-port**

Displays the port used to communicate with the load balancing device.

**--header****-h**

Specifies whether column headings are displayed when the **--long** option is used. The default value is **true**. To suppress the headings, set the **--header** option to **false**.

## Operands

**name**

The name of the load balancer for which you want to display details.

## Examples

### Example 1 Listing Physical Load Balancers for a Domain

This example lists all physical load balancers defined for a domain.

```
asadmin> list-http-lbs

lb1
lb2
Command list-http-lbs executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

---

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-http-lb\(1\)](#), [delete-http-lb\(1\)](#)

# list-http-listeners

Lists the existing network listeners

## Synopsis

```
asadmin [asadmin-options] list-http-listeners [--help]
[target]
```

## Description

The **list-http-listeners** subcommand lists the existing network listeners.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Restricts the listing to network listeners for a specified target. Valid values are as follows:

**server**

Lists the netowrk listeners for the default server instance. This is the default value.

### configuration-name

Lists the network listeners for the specified configuration.

### cluster-name

Lists the network listeners for all server instances in the specified cluster.

### instance-name

Lists the network listeners for the specified server instance.

# Examples

## Example 1 Listing Network Listeners

The following command lists all the network listeners for the server instance:

```
asadmin> list-http-listeners
http-listener-1
http-listener-2
admin-listener
Command list-http-listeners executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-http-listener\(1\)](#), [delete-http-listener\(1\)](#)

# list-iiop-listeners

Lists the existing IIOP listeners

## Synopsis

```
asadmin [asadmin-options] list-iiop-listeners [--help]
[target]
```

## Description

The **list-iiop-listeners** subcommand lists the existing IIOP listeners. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

This operand specifies the target for which the IIOP listeners are to be listed. Valid values are:

**server**

Lists the listeners in the default server instance **server** and is the default value.

### configuration\_name

Lists the listeners in the specified configuration.

### cluster\_name

Lists the listeners in the specified cluster.

### instance\_name

Lists the listeners in a particular server instance.

# Examples

## Example 1 Using the list-iiop-listeners subcommand

The following command lists all the IIOP listeners for the server instance:

```
asadmin> list-iiop-listeners
orb-listener-1
SSL
SSL_MUTUALAUTH
sample_iiop_listener
Command list-iiop-listeners executed successfully.
```

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-iiop-listener\(1\)](#), [delete-iiop-listener\(1\)](#)

# list-instances

Lists Eclipse GlassFish instances in a domain

## Synopsis

```
asadmin [asadmin-options] list-instances [--help]
[--timeoutmsec timeout]
[--long={false|true} | --nostatus={false|true}]
[--standaloneonly={false|true} | target]
```

## Description

The **list-instances** subcommand lists Eclipse GlassFish instances in a domain. The list can be filtered by cluster, instance, node, or configuration.

The subcommand displays every Eclipse GlassFish instance in the specified target, regardless of how each instance was created. For example, this subcommand lists instances that were created by using the [create-instance\(1\)](#) subcommand and by using the [create-local-instance\(1\)](#) subcommand.

By default, the subcommand indicates whether each instance that is listed is running. Options of this subcommand control the information that is displayed for each instance.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--timeoutmsec**

The time limit in milliseconds for determining the status of instances. The default is 2,000, which is equivalent to 2 seconds.

**--long**

**-l**

Specifies whether detailed information is displayed for each instance that is listed.

The **--long** option and **--nostatus** option are mutually exclusive. If both options are specified in the

same command, an error occurs.

Valid values are as follows:

#### **true**

The following details are displayed for each instance that is listed:

- The name of the instance
- The name of the host where the instance's node resides
- The HTTP port on which the instance listens for administration requests
- The process identifier (PID) of the instance process or -1 if the instance is not running
- The name of the cluster of which the instance is a member, if any
- The state of the instance, which is **running** or **not running**

When an instance is listed, some configuration changes in the domain administration server (DAS) for the instance might not have been applied to the instance itself. In this situation, the commands that are required to apply the changes are listed adjacent to the state of the instance. The maximum number of commands that are listed for an instance is 10.

#### **false**

Only the name of the instance and an indication of whether the instance is running are displayed (default). The length of time that the instance has been running is not displayed.

#### **--nostatus**

Specifies whether information about whether instances are running is suppressed.

The **--long** option and **--nostatus** option are mutually exclusive. If both options are specified in the same command, an error occurs.

Valid values are as follows:

#### **true**

Information about whether instances are running is suppressed. Only the name of each instance is displayed.

#### **false**

Information about whether instances are running is displayed (default).

#### **--standaloneonly**

Specifies whether only standalone instances are listed.

The **--standaloneonly** option and the target operand and are mutually exclusive. If both the **--standaloneonly** option and the target operand are specified in the same command, an error occurs.

Valid values are as follows:

**true**

Only standalone instances are listed.

**false**

All instances in the specified target are listed (default).

# Operands

**target**

Filters the list of Eclipse GlassFish instances by specifying the target for which instances are listed. The target operand and the `--standaloneonly` option are mutually exclusive. If both the target operand and the `--standaloneonly` option are specified in the same command, an error occurs. Valid values are as follows:

**domain**

Lists all instances in the domain (default).

**cluster-name**

Lists the instances that are members of the specified cluster.

**instance-name**

Lists only the specified instance.

**node-name**

Lists the instances that reside on the specified node.

**configuration-name**

Lists all instances whose configuration is defined by the specified named configuration.

# Examples

## Example 1 Listing Basic Information About All Eclipse GlassFish Instances in a Domain

This example lists the name and status of all Eclipse GlassFish instances in the current domain.

```
asadmin> list-instances
pmd-i-sj02 running
yml-i-sj02 running
pmd-i-sj01 running
yml-i-sj01 running
pmdsa1 not running
```

Command list-instances executed successfully.

## Example 2 Listing Detailed Information About All Eclipse GlassFish Instances in a Domain

This example lists detailed information about all Eclipse GlassFish instances in the current domain.

```
asadmin> list-instances --long=true
NAME      HOST      PORT    PID    CLUSTER      STATE
pmd-i-sj01  sj01     24848  31310  pmdcluster  running
yml-i-sj01  sj01     24849  25355  ymlcluster   running
pmdsa1     localhost 24848   -1     ---        not running
pmd-i-sj02  sj02     24848  22498  pmdcluster  running
yml-i-sj02  sj02     24849  20476  ymlcluster   running
ymlsa1     localhost 24849   -1     ---        not running
Command list-instances executed successfully.
```

## Example 3 Displaying the Status of an Instance

This example displays status of the instance **pmd-i-sj01**, which is running.

```
asadmin> list-instances pmd-i-sj01
pmd-i-sj01 running
Command list-instances executed successfully.
```

## Example 4 Listing Only Standalone Instances in a Domain

This example lists only the standalone instances in the current domain.

```
asadmin> list-instances --standaloneonly=true  
pmdsa1 not running  
Command list-instances executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#)

# list-jacc-providers

Enables administrators to list JACC providers defined for a domain

## Synopsis

```
asadmin [asadmin-options] list-jacc-providers [--help]
[target]
```

## Description

The **list-jacc-providers** subcommand enables administrators to list the JACC providers defined for a domain. JACC providers are defined as **jacc-provider** elements in the **security-service** element in the domain's **domain.xml** file. JACC providers can be created using the Eclipse GlassFish Admin Console or the **create-jacc-provider** subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

## Operands

### target

Specifies the target for which you want to list JACC providers. The following values are valid:

#### server

Lists the JACC providers on the default server instance. This is the default value.

#### configuration\_name

Lists the JACC providers in the specified configuration.

#### cluster\_name

Lists the JACC providers on all server instances in the specified cluster.

**instance\_name**

Lists the JACC providers on a specified server instance.

## Examples

### Example 1 Listing JACC providers

The following example shows how to list JACC providers for the default domain.

```
asadmin> list-jacc-providers
default
simple
testJACC

Command list-jacc-providers executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jacc-provider\(1\)](#), [delete-jacc-provider\(1\)](#)

# list-javamail-resources

Lists the existing JavaMail session resources

## Synopsis

```
asadmin [asadmin-options] list-javamail-resources [--help]  
[target]
```

## Description

The **list-javamail-resources** subcommand lists the existing JavaMail session resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

This operand specifies the target for which the JavaMail session resources are to be listed. Valid values are:

**server**

Lists the resources for the default server instance. This is the default value.

**domain**

Lists the resources for the domain.

**cluster\_name**

Lists the resources for the specified cluster.

**instance\_name**

Lists the resources for a particular server instance.

# Examples

## Example 1 Listing JavaMail Resources

This example lists the JavaMail session resources for the server instance.

```
asadmin> list-javamail-resources  
mail/MyMailSession  
Command list-javamail-resources executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-javamail-resource\(1\)](#), [delete-javamail-resource\(1\)](#)

# list-jdbc-connection-pools

Lists all JDBC connection pools

## Synopsis

```
asadmin [asadmin-options] list-jdbc-connection-pools [--help]
```

## Description

The `list-jdbc-connection-pools` subcommand lists the current JDBC connection pools.

This subcommand is supported in the remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Examples

### Example 1 Listing the JDBC Connection Pools

This example lists the existing JDBC connection pools.

```
asadmin> list-jdbc-connection-pools
sample_derby_pool
__TimerPool
Command list-jdbc-connection-pools executed successfully.
```

## Exit Status

`0`

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jdbc-connection-pool\(1\)](#), [delete-jdbc-connection-pool\(1\)](#)

# list-jdbc-resources

Lists all JDBC resources

## Synopsis

```
asadmin [asadmin-options] list-jdbc-resources [--help]
[target target]
```

## Description

The **list-jdbc-resources** subcommand displays a list of the existing JDBC resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

## Operands

### --target

This operand specifies which JDBC resources you can list. Usage of this operand is optional. Valid values are:

#### server

Lists the JDBC resources in the current server and is the default.

#### domain

Lists the JDBC resources in the current domain.

#### cluster\_name

Lists the JDBC resources in a cluster.

#### instance\_name

Lists the JDBC resources for a particular instance.

# Examples

## Example 1 Listing the JDBC Resources

This example lists the current JDBC resources.

```
asadmin> list-jdbc-resources
jdbc/DerbyPool
Command list-jdbc-resources executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jdbc-resource\(1\)](#), [delete-jdbc-resource\(1\)](#)

# list-jmsdest

Lists the existing JMS physical destinations

## Synopsis

```
asadmin [asadmin-options] list-jmsdest [--help]
[--desttype type]
[target]
```

## Description

The **list-jmsdest** subcommand lists the Java Message Service (JMS) physical destinations.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --desttype

The type of JMS destination to be listed. Valid values are **topic** and **queue**.

## Operands

### target

Restricts the listing to physical destinations for a specified target. Valid values are as follows:

#### server

Lists the physical destinations for the default server instance. This is the default value.

#### configuration-name

Lists the physical destinations in the specified configuration.

**cluster-name**

Lists the physical destinations for every server instance in the specified cluster.

**instance-name**

Lists the physical destinations for the specified server instance.

## Examples

### Example 1 Listing all physical destinations

The following subcommand lists all the physical destinations.

```
asadmin> list-jmsdest
PhysicalQueue
PhysicalTopic
Command list-jmsdest executed successfully.
```

### Example 2 Listing all physical destinations of a specified type

The following subcommand lists all physical topics.

```
asadmin> list-jmsdest --desttype topic
PhysicalTopic
Command list-jmsdest executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jmsdest\(1\)](#), [delete-jmsdest\(1\)](#), [flush-jmsdest\(1\)](#)



# list-jms-hosts

Lists the existing JMS hosts

## Synopsis

```
asadmin [asadmin-options] list-jms-hosts [--help]
[--target target]
```

## Description

The **list-jms-hosts** subcommand lists the existing Java Message Service (JMS) hosts for the JMS service.

This subcommand is supported in remote mode only. Remote **asadmin** subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Restricts the listing to JMS hosts for a specified target. Valid values are as follows:

##### server

Lists the JMS hosts for the default server instance. This is the default value.

##### configuration-name

Lists the JMS hosts for the specified configuration.

##### cluster-name

Lists the JMS hosts for all server instances in the specified cluster.

##### instance-name

Lists the JMS hosts for the specified server instance.

# Examples

## Example 1 Listing all JMS hosts

The following subcommand lists the JMS hosts for the JMS service.

```
asadmin> list-jms-hosts server-config
default_JMS_host
MyNewHost
Command list-jms-hosts executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jms-host\(1\)](#), [delete-jms-host\(1\)](#), [jms-ping\(1\)](#)

# list-jms-resources

Lists the JMS resources

## Synopsis

```
asadmin [asadmin-options] list-jms-resources [--help]
[--restype type]
[target]
```

## Description

The `list-jms-resources` subcommand lists the existing Java Message Service (JMS) resources (destination and connection factory resources).

This subcommand is supported in remote mode only. Remote `asadmin` subcommands require a running domain administration server (DAS).

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--restype`

The JMS resource type can be `jakarta.jms.Topic`, `jakarta.jms.Queue`, `jakarta.jms.ConnectionFactory`, `jakarta.jms.TopicConnectionFactory`, or `jakarta.jms.QueueConnectionFactory`.

## Operands

### target

Restricts the listing to resources for a specified target. Valid values are as follows:

`server`

Lists the resources for the default server instance. This is the default value.

`domain`

Lists the resources for the domain.

**cluster-name**

Lists the resources for every server instance in the specified cluster.

**instance-name**

Lists the resources for the specified server instance.

## Examples

### Example 1 Listing all JMS resources

The following subcommand lists all JMS resources.

```
asadmin> list-jms-resources
jms/Queue
jms/ConnectionFactory
jms/DurableConnectionFactory
jms/Topic
Command list-jms-resources executed successfully.
```

### Example 2 Listing JMS resources of a specified type

The following subcommand lists all `jakarta.jms.ConnectionFactory` resources.

```
asadmin> list-jms-resources --restype jakarta.jms.ConnectionFactory
jms/ConnectionFactory
jms/DurableConnectionFactory
Command list-jms-resources executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jms-resource\(1\)](#), [delete-jms-resource\(1\)](#)

# list-jndi-entries

Browses and queries the JNDI tree

## Synopsis

```
asadmin [asadmin-options] list-jndi-entries [--help]
[--context context_name]
[target]
```

## Description

Use this subcommand to browse and query the JNDI tree.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --context

The name of the JNDI context or subcontext. If context is not specified, all entries in the naming service are returned. If context (such as **ejb**) is specified, all those entries are returned.

## Operands

### target

This operand specifies the JNDI tree to browse. Possible values are as follows:

#### server

Browses the JNDI tree for the default Eclipse GlassFish instance (default). The default instance is the domain administration server (DAS).

#### domain

Browses the JNDI tree for the current domain.

**cluster-name**

Browses the JNDI tree for the specified cluster.

**instance-name**

Browses the JNDI tree for the specified Eclipse GlassFish instance.

## Examples

### Example 1 Browsing the JNDI Tree

This example browses the JNDI tree for the default Eclipse GlassFish instance.

```
asadmin> list-jndi-entries
java:global: com.sun.enterprise.naming.impl.TransientContext
jdbc: com.sun.enterprise.naming.impl.TransientContext
ejb: com.sun.enterprise.naming.impl.TransientContext
com.sun.enterprise.container.common.spi.util.InjectionManager:
com.sun.enterprise.container.common.impl.util.InjectionManagerImpl
```

Command list-jndi-entries executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jndi-resource\(1\)](#), [delete-jndi-resource\(1\)](#), [list-jndi-resources\(1\)](#)

# list-jndi-resources

Lists all existing JNDI resources

## Synopsis

```
list-jndi-resources [--help] [target]
```

## Description

The **list-jndi-resources** subcommand identifies all existing JNDI resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

The target for which the JNDI resources are to be listed. Valid values are as follows:

**server**

Lists the JNDI resources on the default server instance. This is the default value.

### configuration-name

Lists the JNDI resources for the specified configuration.

### cluster-name

Lists the JNDI resources on all server instances in the specified cluster.

### instance-name

Lists the JNDI resources on a specified server instance.

# Examples

## Example 1 Listing JNDI Resources

This example lists the JNDI resources on the default server instance.

```
asadmin> list-jndi-resources
jndi_resource1
jndi_resource2
jndi_resource3
Command list-jndi-resources executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jndi-resource\(1\)](#), [delete-jndi-resource\(1\)](#)

# list-jobs

Lists information about subcommands that were started using `asadmin --detach` or that contain progress information

## Synopsis

```
asadmin [asadmin-options] list-jobs [--help]  
[job_id]
```

## Description

The `list-jobs` subcommand lists information about subcommands that were started using the `asadmin` utility option `--detach` or that contain progress information. The `--detach` option detaches long-running subcommands and executes them in the background in detach mode.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### job\_id

The ID of the job for which you want to list information.

## Examples

### Example 1 Checking Job Status

This example provides information about subcommands that were started using `asadmin --detach` or that contain progress information.

```
asadmin> list-jobs
JOB ID      COMMAND          STATE      EXIT CODE TIME OF COMPLETION
1           create-cluster   COMPLETED  SUCCESS    2013-02-15 16:16:16 PST
2           deploy           COMPLETED  FAILURE    2013-02-15 18:26:30 PST
Command list-jobs executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[attach\(1\)](#), [configure-managed-jobs\(1\)](#)

# list-jvm-options

Lists options for the Java application launcher

## Synopsis

```
asadmin [asadmin-options] list-jvm-options [--help]
[--target target]
[--profiler={false|true}]
```

## Description

The `list-jvm-options` subcommand displays a list of command-line options that are passed to the Java application launcher when Eclipse GlassFish is started.

The options are managed by using the JVM Options page of the Administration Console or by using the `create-jvm-options` and `delete-jvm-options` subcommands.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Specifies the target for which you are listing Java application launcher options. Valid values are as follows:

##### server

Specifies the DAS (default).

##### instance-name

Specifies a Eclipse GlassFish instance.

##### cluster-name

Specifies a cluster.

**configuration-name**

Specifies a named configuration.

**--profiler**

Specifies whether the Java application launcher options to list are for the profiler. Set this option to true only if a profiler has been configured. If this option is set to true and no profiler is configured, an error occurs. The default is false.

## Examples

### Example 1 Listing the Java Application Launcher Options

This example lists the options that are used by the Java application launcher.

```
asadmin> list-jvm-options
-Djava.security.auth.login.config=${com.sun.aas.instanceRoot}/config/login.conf
-XX: LogVMOutput
-XX: UnlockDiagnosticVMOptions
-Dcom.sun.enterprise.config.config_environment_factory_class=
com.sun.enterprise.config.serverbeans.AppserverConfigEnvironmentFactory
-Djavax.net.ssl.keyStore=${com.sun.aas.instanceRoot}/config/keystore.jks
-XX:NewRatio=2
-DANTLR_USE_DIRECT_CLASS_LOADING=true
-Djava.security.policy=${com.sun.aas.instanceRoot}/config/server.policy
-Djdbc.drivers=org.apache.derby.jdbc.ClientDriver
-Djavax.net.ssl.trustStore=${com.sun.aas.instanceRoot}/config/cacerts.jks
-client
-Djava.ext.dirs=${com.sun.aas.javaRoot}/lib/ext${path.separator}${
com.sun.aas.javaRoot}/jre/lib/ext${path.separator}${com.sun.aas.instanceRoot}
/lib/ext${path.separator}${com.sun.aas.derbyRoot}/lib
-Xmx512m
-XX:MaxPermSize=192m
-XX:LogFile=${com.sun.aas.instanceRoot}/logs/jvm.log
Command list-jvm-options executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-jvm-options\(1\)](#), [delete-jvm-options\(1\)](#)

For more information about the Java application launcher, see the reference page for the operating system that you are using:

- Oracle Solaris and Linux: java - the Java application launcher  
(` `<http://docs.oracle.com/javase/6/docs/technotes/tools/solaris/java.html>)
- Windows: java - the Java application launcher  
(` `<http://docs.oracle.com/javase/6/docs/technotes/tools/windows/java.html>)

# list-libraries

Lists library JAR files on Eclipse GlassFish

## Synopsis

```
asadmin [asadmin-options] list-libraries [--help]
[--type={common|ext|app}]
```

## Description

The **list-libraries** subcommand lists library archive files on Eclipse GlassFish.

The **--type** option specifies the library type and the Eclipse GlassFish directory for which libraries are to be listed.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--type**

Specifies the library type and the Eclipse GlassFish directory for which libraries are listed. Valid values are as follows:

**common**

Lists the library files for the Common class loader directory, domain-dir/**lib**. This is the default.

**ext**

Lists the library files for the Java optional package directory, domain-dir/**lib/ext**.

**app**

Lists the library files for the application-specific class loader directory, domain-dir/**lib/applibs**.

For more information about these directories, see "Class Loaders" in Eclipse GlassFish Application Development Guide.

# Examples

## Example 1 Listing Libraries

This example lists the libraries in the application-specific class loader directory on the default server instance.

```
asadmin> list-libraries --type app
mylib.jar
xlib.jar
ylib.jar
zlib.jar
Command list-libraries executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[add-library\(1\), remove-library\(1\)](#)

["Class Loaders" in Eclipse GlassFish Application Development Guide](#)

# list-lifecycle-modules

Lists the lifecycle modules

## Synopsis

```
asadmin [asadmin-options] list-lifecycle-modules [--help]
[target]
```

## Description

The **list-lifecycle-modules** subcommand lists lifecycle modules. A lifecycle module provides a means of running a short or long duration Java-based task at a specific stage in the server life cycle. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Indicates the location where lifecycle modules are to be listed. Valid values are

- **server** - Specifies the default server instance as the target for listing lifecycle modules. **server** is the name of the default server instance and is the default value for this operand.
- **cluster\_name** - Specifies a particular cluster as the target for listing lifecycle modules.
- **instance\_name** - Specifies a particular server instance as the target for listing lifecycle modules.

## Examples

## Example 1 Listing Lifecycle Modules

```
asadmin> list-lifecycle-modules
WSTCPConnectorLCModule
Command list-lifecycle-modules executed successfully
```

`WSTCPConnectorLCModule` is the only lifecycle module listed for the default target, `server`.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-lifecycle-module\(1\)](#), [delete-lifecycle-module\(1\)](#)

# list-log-attributes

Lists all logging attributes defined for a specified target in a domain

## Synopsis

```
asadmin [asadmin-options] list-log-attributes [--help]  
[target]
```

## Description

The `list-log-attributes` subcommand lists all logging attributes currently defined for the specified Eclipse GlassFish domain or target within a domain. The values listed correspond to the values in the `logging.properties` file for the domain.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### target

Valid values are:

- `server` - The default server instance. This is the default value.
- `configuration_name` - The name of a specific configuration.
- `cluster_name` - The name of a target cluster.
- `instance_name` - The name of a target server instance.

## Examples

## Example 1 Listing the Logger Attributes for a Domain

This example lists all loggers attributes for the default domain.

```
asadmin> list-log-attributes
com.sun.enterprise.server.logging.GFFFileHandler.alarms <false>
com.sun.enterprise.server.logging.GFFFileHandler.file \
<${com.sun.aas.instanceRoot}/logs/server.log>
com.sun.enterprise.server.logging.GFFFileHandler.flushFrequency ①
com.sun.enterprise.server.logging.GFFFileHandler.formatter \
<com.sun.enterprise.server.logging.UniformLogFormatter>
com.sun.enterprise.server.logging.GFFFileHandler.logtoConsole <false>
com.sun.enterprise.server.logging.GFFFileHandler.maxHistoryFiles ②
com.sun.enterprise.server.logging.GFFFileHandler.retainErrorsStaticsForHours ②
com.sun.enterprise.server.logging.GFFFileHandler.rotationLimitInBytes
com.sun.enterprise.server.logging.GFFFileHandler.rotationTimeLimitInMinutes ②
com.sun.enterprise.server.logging.SyslogHandler.useSystemLogging <false>
handlers <java.util.logging.ConsoleHandler>
java.util.logging.ConsoleHandler.formatter \
<com.sun.enterprise.server.logging.UniformLogFormatter>
java.util.logging.FileHandler.count ①
java.util.logging.FileHandler.formatter <java.util.logging.XMLFormatter>
java.util.logging.FileHandler.limit
java.util.logging.FileHandler.pattern <%h/java%u.log>
log4j.logger.org.hibernate.validator.util.Version <warn>
```

Command list-log-attributes executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[collect-log-files\(1\)](#), [list-log-levels\(1\)](#), [rotate-log\(1\)](#), [set-log-attributes\(1\)](#), [set-log-levels\(1\)](#)

["Administering the Logging Service"](#) in Eclipse GlassFish Administration Guide

# list-loggers

Lists existing loggers

## Synopsis

```
asadmin [asadmin-options] list-loggers [--help]
```

## Description

The `list-loggers` subcommand lists the existing Eclipse GlassFish loggers. Internal loggers are not listed. The `list-loggers` subcommand lists the logger name, subsystem, and description.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Examples

### Example 1 Listing the Loggers

This example lists the logger name, subsystem, and description for each logger. Some lines of output are omitted from this example for readability.

```
asadmin> list-loggers
Logger Name          Subsystem      Logger Description
...
jakarta.enterprise.monitoring    Monitoring   Monitoring Logger
jakarta.enterprise.system.core.ee AS-CORE       Jakarta EE Core Kernel
jakarta.enterprise.system.jmx     JMX          JMX System Logger
jakarta.enterprise.system.tools.admin ADMIN        Administration Services
...
Command list-loggers executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-log-levels\(1\)](#), [set-log-file-format\(1\)](#)

# list-log-levels

Lists the loggers and their log levels

## Synopsis

```
asadmin [asadmin-options] list-log-levels [--help]
[--target target]
```

## Description

The **list-log-levels** subcommand lists the current Eclipse GlassFish loggers and their log levels. This subcommand reports on all the loggers that are listed in the **logging.properties** file. In some cases, loggers that have not been created by the respective containers will appear in the list.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

The server, cluster or server instance for which log levels will be listed.

## Operands

### target

Valid values are:

- `server_name` - Default target is `server`. If no target is specified then log levels are listed for the server.
- `cluster_name` - The name of a target cluster.
- `instance_name` - The name of a target server instance.

# Examples

## Example 1 Listing the Log Levels

This example lists the existing loggers and indicates how their log levels are set.

```
asadmin> list-log-levels
java.util.logging.ConsoleHandler      <FINEST>
jakarta.enterprise.resource.corba <INFO>
jakarta.enterprise.resource.javamail    <INFO>
jakarta.enterprise.resource.jdo     <INFO>
jakarta.enterprise.resource.jms    <INFO>
jakarta.enterprise.resource.jta     <INFO>
jakarta.enterprise.resource.resourceadapter <INFO>
jakarta.enterprise.resource.sqltrace   <FINE>
jakarta.enterprise.resource.webcontainer.jsf.application <INFO>
jakarta.enterprise.resource.webcontainer.jsf.config       <INFO>
jakarta.enterprise.resource.webcontainer.jsf.context     <INFO>
jakarta.enterprise.resource.webcontainer.jsf.facelets   <INFO>
jakarta.enterprise.resource.webcontainer.jsf.lifecycle  <INFO>
jakarta.enterprise.resource.webcontainer.jsf.managedbean <INFO>
jakarta.enterprise.resource.webcontainer.jsf.renderkit   <INFO>
jakarta.enterprise.resource.webcontainer.jsf.resource    <INFO>
jakarta.enterprise.resource.webcontainer.jsf.taglib      <INFO>
jakarta.enterprise.resource.webcontainer.jsf.timing      <INFO>
jakarta.enterprise.system.container.cmp    <INFO>
jakarta.enterprise.system.container.ejb   <INFO>
jakarta.enterprise.system.container.ejb.mdb <INFO>
jakarta.enterprise.system.container.web  <INFO>
jakarta.enterprise.system.core.classloading <INFO>
jakarta.enterprise.system.core.config     <INFO>
jakarta.enterprise.system.core           <INFO>
jakarta.enterprise.system.core.naming    <INFO>
jakarta.enterprise.system.core.security <INFO>
jakarta.enterprise.system.core.selfmanagement <INFO>
jakarta.enterprise.system.core.transaction <INFO>
jakarta.enterprise.system <INFO>
jakarta.enterprise.system.tools.admin    <INFO>
jakarta.enterprise.system.tools.backup   <INFO>
jakarta.enterprise.system.tools.deployment <INFO>
jakarta.enterprise.system.util          <INFO>
jakarta.enterprise.system.webservices.registry <INFO>
jakarta.enterprise.system.webservices.rpc <INFO>
jakarta.enterprise.system.webservices.saaj    <INFO>
javax    <INFO>
javax.org.glassfish.persistence <INFO>
org.apache.catalina      <INFO>
org.apache.coyote        <INFO>
org.glassfish.wasp        <INFO>
org.glassfish.admingui   <INFO>
org.jvnet.hk2.osgiadapter <INFO>
Command list-log-levels executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[collect-log-files\(1\)](#), [list-log-attributes\(1\)](#), [rotate-log\(1\)](#), [set-log-attributes\(1\)](#), [set-log-levels\(1\)](#)

"[Administering the Logging Service](#)" in Eclipse GlassFish Administration Guide

# list-managed-executor-services

Lists managed executor service resources

## Synopsis

```
asadmin [asadmin-options] list-managed-executor-services [--help]
[target]
```

## Description

The **list-managed-executor-services** subcommand lists managed executor service resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Specifies the target for which managed executor service resources are to be listed. Valid targets are:

**server**

Lists the resources on the default server instance. This is the default value.

**domain**

Lists the resources for the domain.

**cluster-name**

Lists the resources on all server instances in the specified cluster.

**instance-name**

Lists the resources on a specified server instance.

# Examples

## Example 1 Listing Managed Executor Service Resources

This example lists managed executor service resources on the default server instance.

```
asadmin> list-managed-executor-services
concurrent/_defaultManagedExecutorService
concurrent/myExecutor1
concurrent/myExecutor2
Command list-managed-executor-services executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-managed-executor-service\(1\)](#), [delete-managed-executor-service\(1\)](#)

# list-managed-scheduled-executor-services

Lists managed scheduled executor service resources

## Synopsis

```
asadmin [asadmin-options] list-managed-scheduled-executor-services [--help]  
[target]
```

## Description

The **list-managed-scheduled-executor-services** subcommand lists managed scheduled executor service resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

## Operands

### target

Specifies the target for which managed scheduled executor service resources are to be listed. Valid targets are:

#### server

Lists the resources on the default server instance. This is the default value.

#### domain

Lists the resources for the domain.

#### cluster-name

Lists the resources on all server instances in the specified cluster.

**instance-name**

Lists the resources on a specified server instance.

## Examples

### Example 1 Listing Managed Scheduled Executor Service Resources

This example lists managed scheduled executor service resources on the default server instance.

```
asadmin> list-managed-scheduled-executor-services
concurrent/_defaultManagedScheduledExecutorService
concurrent/myScheduledExecutor1
concurrent/myScheduledExecutor2
Command list-managed-scheduled-executor-services executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-managed-scheduled-executor-service\(1\)](#), [delete-managed-scheduled-executor-service\(1\)](#)

# list-managed-thread-factories

Lists managed thread factory resources

## Synopsis

```
asadmin [asadmin-options] list-managed-thread-factories [--help]
[target]
```

## Description

The **list-managed-thread-factories** subcommand lists managed thread factory resources.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Specifies the target for which managed thread factory resources are to be listed. Valid targets are:

**server**

Lists the resources on the default server instance. This is the default value.

**domain**

Lists the resources for the domain.

**cluster-name**

Lists the resources on all server instances in the specified cluster.

**instance-name**

Lists the resources on a specified server instance.

# Examples

## Example 1 Listing Managed Thread Factory Resources

This example lists managed thread factory resources on the default server instance.

```
asadmin> list-managed-thread-factories
concurrent/_defaultManagedThreadFactory
concurrent/myThreadFactory1
concurrent/myThreadFactory2
Command list-managed-thread-factories executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-managed-thread-factory\(1\)](#), [delete-managed-thread-factory\(1\)](#)

# list-message-security-providers

Lists all security message providers for the given message layer

## Synopsis

```
asadmin [asadmin-options] list-message-security-providers [--help]
--layer message_layer
[target]
```

## Description

The `list-message-security-providers` subcommand enables administrators to list all security message providers (`provider-config` sub-elements) for the given message layer (`message-security-config` element of `domain.xml`).

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--layer`

The message-layer for which the provider has to be listed. The default value is `HttpServlet`.

## Operands

### target

Restricts the listing to message security providers for a specific target. Valid values include:

`server`

Lists providers for the default server instance `server` and is the default value.

`domain`

Lists providers for the domain.

**cluster**

Lists providers for the server instances in the cluster.

**instance**

Lists providers for a particular server instance.

## Examples

### Example 1 Listing message security providers

The following example shows how to list message security providers for a message layer.

```
asadmin> list-message-security-providers  
--layer SOAP  
XWS_ClientProvider  
ClientProvider  
XWS_ServerProvider  
ServerProvider  
Command list-message-security-providers executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-message-security-provider\(1\)](#), [delete-message-security-provider\(1\)](#)

# list-modules

Lists Eclipse GlassFish modules

## Synopsis

```
asadmin [asadmin-options] list-modules [--help]
```

## Description

The **list-modules** subcommand displays a list of modules that are accessible to the Eclipse GlassFish module subsystem. The version of each module is shown.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Examples

### Example 1 Listing Eclipse GlassFish Modules

This example provides a partial listing of modules that are accessible to the Eclipse GlassFish module subsystem

```
asadmin> list-modules
List Of Modules

Module : org.glassfish.transaction.jts:3.0.0.b66
    Module Characteristics : List of Jars implementing the module
        Jar : file:/home/gfuser/GlassFish/glassfish7/glassfish/modules/jts.jar
    Module Characteristics : Provides to following services
    Module Characteristics : List of imported modules
        Imports : org.glassfish.transaction.jts:3.0.0.b66
Module : com.sun.enterprise.tiger-types-osgi:0.3.96
Module : org.glassfish.bean-validator:3.0.0.JBoss-400Beta3A
Module : org.glassfish.core.kernel:3.0.0.b66
    Module Characteristics : Provides to following services
    Module Characteristics : List of imported modules
        Imports : org.glassfish.core.kernel:3.0.0.b66
    Module Characteristics : List of Jars implementing the module
        Jar : file:/home/gfuser/GlassFish/glassfish7/glassfish/modules/kernel.jar
Module : org.glassfish.common.util:3.0.0.b66
    Module Characteristics : List of Jars implementing the module
        Jar : file:/home/gfuser/GlassFish/glassfish7/glassfish/modules/common-util.jar
    Module Characteristics : Provides to following services
    Module Characteristics : List of imported modules
        Imports : org.glassfish.common.util:3.0.0.b66
...
Command list-modules executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-commands\(1\)](#), [list-components\(1\)](#), [list-containers\(1\)](#)

# list-network-listeners

Lists the existing network listeners

## Synopsis

```
asadmin [asadmin-options] list-network-listeners [--help]
[target]
```

## Description

The **list-network-listeners** subcommand lists the existing network listeners. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

## Operands

### target

Restricts the listing to network listeners for a specified target. Valid values are as follows:

#### server

Lists the network listeners for the default server instance. This is the default value.

#### configuration-name

Lists the network listeners for the specified configuration.

#### cluster-name

Lists the network listeners for all server instances in the specified cluster.

#### instance-name

Lists the network listeners for the specified server instance.

# Examples

## Example 1 Listing Network Listeners

The following command lists all the network listeners for the server instance:

```
asadmin> list-network-listeners
admin-listener
http-listener-1
https-listener-2
Command list-network-listeners executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-network-listener\(1\)](#), [delete-network-listener\(1\)](#)

# list-nodes

Lists all Eclipse GlassFish nodes in a domain

## Synopsis

```
asadmin [asadmin-options] list-nodes [--help]
[--long={false|true}]
```

## Description

The **list-nodes** subcommand lists all Eclipse GlassFish nodes in a domain.

By default, the subcommand displays the following information for each node that is listed:

- The name of the node
- The type of the node, which is one of the following types:::

### CONFIG

The node does not support remote communication.

### DCOM

The node supports communication over the Distributed Component Object Model (DCOM) remote protocol.

### SSH

The node supports communication over secure shell (SSH).

- The name of the host that the node represents

The **--long** option of the subcommand specifies whether the nodes are listed in long format. In long format, the following additional information about each node is displayed:

- The path to the parent of the base installation directory of Eclipse GlassFish on the host that the node represents
- A comma-separated list of the names of the Eclipse GlassFish instances that reside on the node

If the **--terse** option of the **asadmin(1M)** utility is **true** and the **--long** option of the subcommand is **false**, the subcommand lists only the name of each node.

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--long`

`-l`

Specifies whether the nodes are listed in long format.

Possible values are as follows:

`true`

The nodes are listed in long format.

`false`

The nodes are listed in short format (default).

## Examples

### Example 1 Listing Eclipse GlassFish Nodes

This example displays the name, type, and host for all Eclipse GlassFish nodes in the domain `domain1`.

```
asadmin> list-nodes
localhost-domain1 CONFIG localhost
sj02 SSH sj02.example.com
sj01 SSH sj01.example.com
devnode CONFIG localhost
Command list-nodes executed successfully.
```

### Example 2 Listing Only the Names of Eclipse GlassFish Nodes

This example uses the `--terse` option of the `asadmin` utility to list only the names of the Eclipse GlassFish nodes in the domain `domain1`.

```
asadmin> list-nodes --terse=true
localhost-domain1
sj02
sj01
devnode
```

## Example 3 Listing Eclipse GlassFish Nodes in Long Format

This example lists the Eclipse GlassFish nodes in the domain `domain1` in long format.

```
asadmin> list-nodes --long=true
NODE NAME      TYPE      NODE HOST      INSTALL DIRECTORY      REFERENCED BY
localhost-domain1  CONFIG    localhost      /export/glassfish7
sj02           SSH       sj02.example.com  /export/glassfish7  pmd-i2, yml-i2
sj01           SSH       sj01.example.com  /export/glassfish7  pmd-i1, yml-i1
devnode         CONFIG    localhost      /export/glassfish7  pmdsa1
Command list-nodes executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [list-nodes-config\(1\)](#), [list-nodes-dcom\(1\)](#), [list-nodes-ssh\(1\)](#)

# list-nodes-config

Lists all Eclipse GlassFish nodes that do not support remote communication in a domain

## Synopsis

```
asadmin [asadmin-options] list-nodes-config [--help]
[--long={false|true}]
```

## Description

The **list-nodes-config** subcommand lists all Eclipse GlassFish nodes that do not support remote communication in a domain.



To list all nodes in a domain regardless of the type of the node, run the [list-nodes\(1\)](#) subcommand.

By default, the subcommand displays the following information for each node that is listed:

- The name of the node
- The type of the node, which is **CONFIG**
- The name of the host that the node represents

The **--long** option of the subcommand specifies whether the nodes are listed in long format. In long format, the following additional information about each node is displayed:

- The path to the parent of the base installation directory of Eclipse GlassFish on the host that the node represents
- A comma-separated list of the names of the Eclipse GlassFish instances that reside on the node

If the **--terse** option of the [asadmin\(1M\)](#) utility is **true** and the **--long** option of the subcommand is **false**, the subcommand lists only the name of each node.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--long****-l**

Specifies whether the nodes are listed in long format.

Possible values are as follows:

**true**

The nodes are listed in long format.

**false**

The nodes are listed in short format (default).

## Examples

### Example 1 Listing Eclipse GlassFish Nodes

This example displays the name, type, and host for all Eclipse GlassFish nodes that do not support remote communication in the domain `domain1`.

```
asadmin> list-nodes-config
localhost-domain1 CONFIG localhost
devnode CONFIG localhost
Command list-nodes-config executed successfully.
```

### Example 2 Listing Only the Names of Eclipse GlassFish Nodes

This example uses the `--terse` option of the `asadmin` utility to list only the names of the Eclipse GlassFish nodes that do not support remote communication in the domain `domain1`.

```
asadmin> list-nodes-config --terse=true
localhost-domain1
devnode
```

## Example 3 Listing Eclipse GlassFish Nodes in Long Format

This example lists the Eclipse GlassFish nodes that do not support remote communication in the domain `domain1` in long format.

```
asadmin> list-nodes-config --long=true
NODE NAME      TYPE      NODE HOST   INSTALL DIRECTORY   REFERENCED BY
localhost-domain1  CONFIG    localhost /export/glassfish7
devnode        CONFIG    localhost /export/glassfish7  pmdsa1
Command list-nodes-config executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [list-nodes\(1\)](#), [list-nodes-dcom\(1\)](#), [list-nodes-ssh\(1\)](#)

# list-nodes-dcom

Lists all Eclipse GlassFish nodes that support communication over DCOM in a domain

## Synopsis

```
asadmin [asadmin-options] list-nodes-dcom [--help]
[--long={false|true}]
```

## Description

The [list-nodes-dcom](#) subcommand lists all Eclipse GlassFish nodes that support communication over the Distributed Component Object Model (DCOM) remote protocol. The DCOM protocol is available only on Windows systems.



To list all nodes in a domain regardless of the type of the node, run the [list-nodes\(1\)](#) subcommand.

By default, the subcommand displays the following information for each node that is listed:

- The name of the node
- The type of the node, which is [DCOM](#)
- The name of the host that the node represents

The [--long](#) option of the subcommand specifies whether the nodes are listed in long format. In long format, the following additional information about each node is displayed:

- The path to the parent of the base installation directory of Eclipse GlassFish on the host that the node represents
- A comma-separated list of the names of the Eclipse GlassFish instances that reside on the node

If the [--terse](#) option of the [asadmin\(1M\)](#) utility is [true](#) and the [--long](#) option of the subcommand is [false](#), the subcommand lists only the name of each node.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--long****-l**

Specifies whether the nodes are listed in long format.

Possible values are as follows:

**true**

The nodes are listed in long format.

**false**

The nodes are listed in short format (default).

## Examples

### Example 1 Listing Eclipse GlassFish Nodes

This example displays the name, type, and host for all Eclipse GlassFish nodes that support communication over DCOM in a domain.

```
asadmin> list-nodes-dcom
xkyd  DCOM  xkyd.example.com
wpmdl2  DCOM  wpmdl2.example.com
wpmdl1  DCOM  wpmdl1.example.com
Command list-nodes-dcom executed successfully.
```

### Example 2 Listing Only the Names of Eclipse GlassFish Nodes

This example uses the **--terse** option of the **asadmin** utility to list only the names of the Eclipse GlassFish nodes that support communication over DCOM in a domain.

```
asadmin> list-nodes-dcom --terse=true
xkyd
wpmdl2
wpmdl1
```

## Example 3 Listing Eclipse GlassFish Nodes in Long Format

This example lists the Eclipse GlassFish nodes that support communication over DCOM in a domain in long format.

```
asadmin> list-nodes-dcom --long=true
NODE NAME    TYPE    NODE HOST          INSTALL DIRECTORY  REFERENCED BY
xkyd         DCOM    xkyd.example.com  C:\glassfish7
wpmdl2       DCOM    wpmdl2.example.com C:\glassfish7      wdi2
wpmdl1       DCOM    wpmdl1.example.com C:\glassfish7      wdi1
Command list-nodes-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [list-nodes\(1\)](#), [list-nodes-config\(1\)](#), [list-nodes-dcom\(1\)](#)

# list-nodes-ssh

Lists all Eclipse GlassFish nodes that support communication over SSH in a domain

## Synopsis

```
asadmin [asadmin-options] list-nodes-ssh [--help]
[--long={false|true}]
```

## Description

The [list-nodes-ssh](#) subcommand lists all Eclipse GlassFish nodes that support communication over secure shell (SSH) in a domain.



To list all nodes in a domain regardless of the type of the node, run the [list-nodes\(1\)](#) subcommand.

By default, the subcommand displays the following information for each node that is listed:

- The name of the node
- The type of the node, which is [SSH](#)
- The name of the host that the node represents

The [--long](#) option of the subcommand specifies whether the nodes are listed in long format. In long format, the following additional information about each node is displayed:

- The path to the parent of the base installation directory of Eclipse GlassFish on the host that the node represents
- A comma-separated list of the names of the Eclipse GlassFish instances that reside on the node

If the [--terse](#) option of the [asadmin\(1M\)](#) utility is [true](#) and the [--long](#) option of the subcommand is [false](#), the subcommand lists only the name of each node.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--long****-l**

Specifies whether the nodes are listed in long format. Possible values are as follows:

**true**

The nodes are listed in long format.

**false**

The nodes are listed in short format (default).

## Examples

### Example 1 Listing Eclipse GlassFish Nodes

This example displays the name, type, and host for all Eclipse GlassFish nodes that support communication over SSH in a domain.

```
asadmin> list-nodes-ssh
sj02  SSH  sj02.example.com
sj01  SSH  sj01.example.com
Command list-nodes-ssh executed successfully.
```

### Example 2 Listing Only the Names of Eclipse GlassFish Nodes

This example uses the **--terse** option of the **asadmin** utility to list only the names of the Eclipse GlassFish nodes that support communication over SSH in a domain.

```
asadmin> list-nodes-ssh --terse=true
sj02
sj01
```

## Example 3 Listing Eclipse GlassFish Nodes in Long Format

This example lists the Eclipse GlassFish nodes that support communication over SSH in a domain in long format.

```
asadmin> list-nodes-ssh --long=true
NODE NAME    TYPE    NODE HOST          INSTALL DIRECTORY   REFERENCED BY
sj02         SSH     sj02.example.com /export/glassfish7 pmd-i-sj02, yml-i-sj02
sj01         SSH     sj01.example.com /export/glassfish7 pmd-i-sj01, yml-i-sj01
Command list-nodes-ssh executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-dcom\(1\)](#), [create-node-config\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [list-nodes\(1\)](#), [list-nodes-config\(1\)](#), [list-nodes-dcom\(1\)](#)

# list-password-aliases

Lists all password aliases

## Synopsis

```
asadmin [asadmin-options] list-password-aliases [--help]
```

## Description

This subcommand lists all of the password aliases.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Examples

### Example 1 Listing all password aliases

```
asadmin> list-password-aliases  
jmspassword-alias  
Command list-password-aliases executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[create-password-alias\(1\)](#), [delete-password-alias\(1\)](#), [update-password-alias\(1\)](#)

# list-persistence-types

Lists registered persistence types for HTTP sessions and SFSB instances

## Synopsis

```
asadmin [asadmin-options] list-persistence-types [--help]  
--type={web|ejb}
```

## Description

The `list-persistence-types` subcommand lists registered persistence types for HTTP sessions and stateful session bean (SFSB) instances. The built-in persistence types are `memory`, `file`, and `replicated`. The `memory` type does not apply to SFSB instances.

Other persistence types can be added using the `StrategyBuilder` class. For more information, see the [Eclipse GlassFish Add-On Component Development Guide](#).

To set the persistence type for HTTP sessions, use the `set` subcommand to set the `persistence-type` attribute. For example:

```
asadmin> set c1-config.availability-service.web-container-availability.persistence-  
type=file
```

To set the persistence type for SFSB instances without availability enabled, use the `set` subcommand to set the `sfsb-persistence-type` attribute. For example:

```
asadmin> set c1-config.availability-service.ejb-container-availability.sfsb-persistence-  
type=file
```

To set the persistence type for SFSB instances with availability enabled, use the `set` subcommand to set the `sfsb-ha-persistence-type` attribute. For example:

```
asadmin> set  
c1-config.availability-service.ejb-container-availability.sfsb-ha-persistence-  
type=replicated
```

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

`--type`

Specifies the type of sessions for which persistence types are listed. Allowed values are as follows:

- `web` — Lists persistence types for HTTP sessions.
- `ejb` — Lists persistence types for SFSB instances.

# Examples

## Example 1 Listing Persistence Types for HTTP Sessions

This example lists persistence types for HTTP sessions.

```
asadmin> list-persistence-types --type=web
memory
file
replicated

Command list-persistence-types executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

# See Also

[asadmin\(1M\)](#)

[get\(1\)](#), [list\(1\)](#), [set\(1\)](#)

[Eclipse GlassFish Add-On Component Development Guide](#)

# list-protocol-filters

Lists the existing protocol filters

## Synopsis

```
asadmin [asadmin-options] list-protocol-filters [--help]
[--target server]
protocol-name
```

## Description

The `list-protocol-filters` subcommand lists the existing protocol filters. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

### target

Restricts the listing to protocol filters for a specified target. Valid values are as follows:

`server`

Lists the protocol filters for the default server instance. This is the default value.

### configuration-name

Lists the protocol filters for the specified configuration.

### cluster-name

Lists the protocol filters for all server instances in the specified cluster.

### instance-name

Lists the protocol filters for the specified server instance.

# Operands

## protocol-name

The name of the protocol for which to list protocol filters.

## Examples

### Example 1 Listing Protocol Filters

The following command lists all the protocol filters for the server instance:

```
asadmin> list-protocol-filters http1
http1-filter
https1-filter
Command list-protocol-filters executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-protocol-filter\(1\)](#), [delete-protocol-filter\(1\)](#)

# list-protocol-finders

Lists the existing protocol finders

## Synopsis

```
asadmin [asadmin-options] list-protocol-finders [--help]
[--target server]
protocol-name
```

## Description

The **list-protocol-finders** subcommand lists the existing protocol finders. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### target

Restricts the listing to protocol finders for a specified target. Valid values are as follows:

**server**

Lists the protocol finders for the default server instance. This is the default value.

### configuration-name

Lists the protocol finders for the specified configuration.

### cluster-name

Lists the protocol finders for all server instances in the specified cluster.

### instance-name

Lists the protocol finders for the specified server instance.

# Operands

## protocol-name

The name of the protocol for which to list protocol finders.

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-protocol-finder\(1\)](#), [delete-protocol-finder\(1\)](#)

# list-protocols

Lists the existing protocols

## Synopsis

```
asadmin [asadmin-options] list-protocols [--help]  
[target]
```

## Description

The **list-protocols** subcommand lists the existing protocols. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

Restricts the listing to protocols for a specified target. Valid values are as follows:

**server**

Lists the protocols for the default server instance. This is the default value.

### configuration-name

Lists the protocols for the specified configuration.

### cluster-name

Lists the protocols for all server instances in the specified cluster.

### instance-name

Lists the protocols for the specified server instance.

# Examples

## Example 1 Listing Protocols

The following command lists all the protocols for the server instance:

```
asadmin> list-protocols
admin-listener
http-1
http-listener-1
http-listener-2
Command list-protocols executed successfully.
```

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-protocol\(1\)](#), [delete-protocol\(1\)](#)

# list-resource-adapter-configs

Lists the names of the current resource adapter configurations

## Synopsis

```
asadmin [asadmin-options] list-resource-adapter-configs [--help]
[--raname raname] [--verbose {false|true}]
```

## Description

This command lists the configuration information in the `domain.xml` for the connector module. It lists an entry called `resource-adapter-config` in the `domain.xml` file. If the `--raname` option is specified, only the resource adapter configurations for the specified connector module are listed.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --raname

Specifies the connector module name.

#### --verbose

Lists the properties that are configured. Default value is false.

## Examples

### Example 1 Listing the Resource Adapter Configurations

This example lists the current resource adapter configurations.

```
asadmin> list-resource-adapter-configs  
ra1  
ra2  
Command list-resource-adapter-configs executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-resource-adapter-config\(1\)](#), [delete-resource-adapter-config\(1\)](#)

# list-resource-refs

Lists existing resource references

## Synopsis

```
asadmin [asadmin-options] list-resource-refs [--help]
[target]
```

## Description

The **list-resource-refs** subcommand lists all resource references in a cluster or an unclustered server instance. This effectively lists all the resources (for example, JDBC resources) available in the JNDI tree of the specified target.

The target instance or instances in the cluster need not be running or available for this subcommand to succeed.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

The target for which you are listing the resource references. Valid targets are as follows:

**server**

Lists the resource references for the default server instance and is the default target.

**cluster\_name**

Lists the resource references for every server instance in the cluster.

**instance\_name**

Lists the resource references for the named unclustered server instance.

## Examples

### Example 1 Listing Resource References for a Cluster

This example lists resource references for the cluster `cluster1`.

```
asadmin> list-resource-refs cluster1
jms/Topic
Command list-resource-refs executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-resource-ref\(1\)](#), [delete-resource-ref\(1\)](#)

# list-secure-admin-internal-users

Lists the user names that the Eclipse GlassFish DAS and instances use to authenticate with each other and to authorize admin operations.

## Synopsis

```
asadmin [asadmin-options] list-secure-admin-internal-users [--help]
[--long={false|true}]
[--output output]
[--header={false|true}]
[name]
```

## Description

The `list-secure-admin-internal-users` subcommand lists the user names that the Eclipse GlassFish DAS and instances use to authenticate with each other and to authorize admin operations.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

`-?`

Displays the help text for the subcommand.

#### --long

`-l`

Displays detailed information about each internal user. The default value is `false`.

#### --output

`-o`

Displays specific details about each internal user. Use a comma-separated list to specify the details you want to display and their order. The values are case-insensitive. Possible values are as follows:

#### username

Displays the user name for the internal user.

#### password-alias

Displays the password alias for the internal user.

**--header****-h**

Specifies whether column headings are displayed when the `--long` option is used. The default value is `true`. To suppress the headings, set the `--header` option to `false`.

## Operands

**name**

The user name for the internal user for which you want to display details.

## Examples

### Example 1 Listing the User Name for Secure Admin

This example lists the user names that the Eclipse GlassFish DAS and instances use to authenticate with each other and to authorize admin operations.

```
asadmin> list-secure-admin-internal-users
```

```
Command list-secure-admin-internal-users executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)[enable-secure-admin\(1\)](#), [enable-secure-admin-internal-user\(1\)](#)

# list-secure-admin-principals

Lists the certificates for which Eclipse GlassFish accepts admin requests from clients.

## Synopsis

```
asadmin [asadmin-options] list-secure-admin-principals [--help]
[--long={false|true}]
[--output output]
[--header={false|true}]
[name]
```

## Description

The `list-secure-admin-principals` subcommand lists the certificates for which Eclipse GlassFish accepts admin requests from clients.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

`-?`

Displays the help text for the subcommand.

#### --long

`-l`

Displays detailed information about the certificates for which Eclipse GlassFish accepts admin requests from clients. The default value is `false`.

#### --output

`-o`

Displays specific details about the certificates for which Eclipse GlassFish accepts admin requests from clients. Use a comma-separated list to specify the details you want to display and their order. The values are case-insensitive. Possible values are as follows:

#### DN

Displays the distinguished name (DN) of each certificate.

**--header****-h**

Specifies whether column headings are displayed when the **--long** option is used. The default value is **true**. To suppress the headings, set the **--header** option to **false**.

## Operands

### name

The distinguished name of the certificate, specified as a comma-separated list in quotes. For example: "CN=system.amer.oracle.com,OU=GlassFish,O=Oracle Corporation,L=Santa Clara,ST=California,C=US".

## Examples

### Example 1 Listing the Certificates

This example lists the certificates for which Eclipse GlassFish accepts admin requests from clients.

```
asadmin> list-secure-admin-principals
CN=localhost,OU=GlassFish,O=Oracle Corporation,L=Santa Clara,ST=California,C=US
CN=localhost-instance,OU=GlassFish,O=Oracle Corporation,L=Santa Clara,ST=California,C=US
Command list-secure-admin-principals executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)[enable-secure-admin\(1\)](#), [enable-secure-admin-principal\(1\)](#)

# list-sub-components

Lists EJB or servlet components in a deployed module or module of a deployed application

## Synopsis

```
asadmin [asadmin-options] list-sub-components [--help]
[--type type]
[--appname appname] [--resources]
modulename
```

## Description

The **list-sub-components** subcommand lists EJB or servlet components in a deployed module or in a module of a deployed application. If a module is not specified, all modules are listed. The **--appname** option functions only when the specified module is stand-alone. To display a specific module in an application, you must specify the module name with the **--appname** option.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

**-?**

Displays the help text for the subcommand.

#### --type

Specifies the type of component to be listed. The options are **ejbs** and  **servlets**. If nothing is specified, then all of the components are listed.

#### --appname

Identifies the name of the application. This option is required when the desired output is the subcomponents of an embedded module of a deployed application.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see " [Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

**--resources**

Lists the application-scoped resources for each subcomponent.

# Operands

## modulename

Specifies the name of the module containing the subcomponent.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see "[Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

# Examples

## Example 1 Listing Subcomponents

This example lists the subcomponents of the `MEjbApp` application within the `mejb.jar` module.

```
asadmin> list-sub-components --appname MEjbApp mejb.jar
MEJBBean <StatelessSessionBean>
Command list-sub-components executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

# See Also

[asadmin\(1M\)](#)

[disable\(1\)](#), [enable\(1\)](#), [list-components\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# list-supported-cipher-suites

Enables administrators to list the cipher suites that are supported and available to a specified Eclipse GlassFish target

## Synopsis

```
asadmin [asadmin-options] list-supported-cipher-suites [--help]
[--target target]
```

## Description

The **list-supported-cipher-suites** subcommand enables administrators to list the cipher suites that are supported and available to a specified Eclipse GlassFish target. The cipher suites that may be available in addition to the default SSL/TLS providers that are bundled with Eclipse GlassFish packages will vary depending on the third-party provider.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

Specifies the target for which you want to list cipher suites. The following values are valid:

##### server

Lists the cipher suites for the default server instance. This is the default value.

##### configuration\_name

Lists the cipher suites for the specified configuration.

##### cluster\_name

Lists the cipher suites for all server instances in the specified cluster.

##### instance\_name

Lists the cipher suites for a specified server instance.

# Examples

## Example 1 Listing cipher suites

The following example shows how to list cipher suites for the default domain.

```
asadmin> list-supported-cipher-suites
SSL_RSA_WITH_RC4_128_MD5
SSL_RSA_WITH_RC4_128_SHA
TLS_RSA_WITH_AES_128_CBC_SHA
TLS_DHE_RSA_WITH_AES_128_CBC_SHA
TLS_DHE_DSS_WITH_AES_128_CBC_SHA
SSL_RSA_WITH_3DES_EDE_CBC_SHA
SSL_DHE_RSA_WITH_3DES_EDE_CBC_SHA
SSL_DHE_DSS_WITH_3DES_EDE_CBC_SHA
SSL_RSA_WITH_DES_CBC_SHA
SSL_DHE_RSA_WITH_DES_CBC_SHA
SSL_DHE_DSS_WITH_DES_CBC_SHA
SSL_RSA_EXPORT_WITH_RC4_40_MD5
SSL_RSA_EXPORT_WITH_DES40_CBC_SHA
SSL_DHE_RSA_EXPORT_WITH_DES40_CBC_SHA
SSL_DHE_DSS_EXPORT_WITH_DES40_CBC_SHA
SSL_RSA_WITH_NULL_MD5
SSL_RSA_WITH_NULL_SHA
SSL_DH_anon_WITH_RC4_128_MD5
TLS_DH_anon_WITH_AES_128_CBC_SHA
SSL_DH_anon_WITH_3DES_EDE_CBC_SHA
SSL_DH_anon_WITH_DES_CBC_SHA
SSL_DH_anon_EXPORT_WITH_RC4_40_MD5
SSL_DH_anon_EXPORT_WITH_DES40_CBC_SHA
```

Command list-supported-cipher-suites executed successfully.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

# list-system-properties

Lists the system properties of the domain, configuration, cluster, or server instance

## Synopsis

```
asadmin [asadmin-options] list-system-properties [--help]
[target]
```

## Description

Shared or clustered server instances will often need to override attributes defined in their referenced configuration. Any configuration attribute in a server instance can be overridden through a system property of the corresponding name. This list-system-properties subcommand lists the system properties of a domain, configuration, cluster, or server instance.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

## Operands

### target

This restricts the listing to system properties for a specific target. Valid values are:

#### domain

Lists the system properties defined for the domain.

#### configuration\_name

Lists the system properties for the named configuration as well as those the cluster inherits from the domain.

#### cluster\_name

Lists the system properties defined for the named cluster as well as those the cluster inherits

from its configuration and the domain.

#### **instance\_name**

Lists the system properties defined for the named server instance as well as those the server inherits from its cluster (if the instance is clustered), its configuration, and the domain.

## Examples

### Example 1 Listing System Properties

This example lists the system properties on `localhost`.

```
asadmin> list-system-properties
http-listener-port=1088
Command list-system-properties executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-system-properties\(1\)](#), [delete-system-property\(1\)](#)

# list-threadpools

Lists all the thread pools

## Synopsis

```
asadmin [asadmin-options] list-threadpools [--help]
target
```

## Description

The **list-threadpools** subcommand lists the Eclipse GlassFish thread pools.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

This operand specifies the target for which you are listing thread pools. This operand is required.

Valid values are as follows:

**server**

Lists the thread pools for the default Eclipse GlassFish instance **server**.

### configuration-name

Lists the thread pools for the named configuration.

### cluster-name

Lists the thread pools for every instance in the cluster.

### instance-name

Lists the thread pools for a particular instance.

# Examples

## Example 1 Listing Thread Pools

This example lists the current thread pools for the default instance `server`.

```
asadmin> list-threadpools server
admin-thread-pool
http-thread-pool
thread-pool-1
Command list-threadpools executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-threadpool\(1\)](#), [delete-threadpool\(1\)](#)

# list-timers

Lists all of the persistent timers owned by server instance(s)

## Synopsis

```
asadmin [asadmin-options] list-timers [--help]  
[target]
```

## Description

The **list-timers** subcommand lists the persistent timers owned by a specific server instance or a cluster of server instances. This command is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Operands

### target

The target is either a standalone server instance or a cluster. If the target is the stand-alone instance, then the number of timers owned by the instance is listed. If the target is a cluster, then the number of timers owned by each instance in the cluster is listed. The default target is **server**, the default server instance.

## Examples

### Example 1 Listing Current Timers in a Server Instance

This example lists persistent timers in a particular standalone server instance. There is one currently active timer set.

```
asadmin> list-timers server
```

```
1
```

The `list-timers` command was executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[migrate-timers\(1\)](#)

[Using the Timer Service in The Jakarta EE Tutorial](#)

["EJB Timer Service" in Eclipse GlassFish Application Development Guide](#)

# list-transports

Lists the existing transports

## Synopsis

```
asadmin [asadmin-options] list-transports [--help]
[target]
```

## Description

The `list-transports` subcommand lists the existing transports. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### target

Restricts the listing to transports for a specified target. Valid values are as follows:

`server`

Lists the transports for the default server instance. This is the default value.

### configuration-name

Lists the transports for the specified configuration.

### cluster-name

Lists the transports for all server instances in the specified cluster.

### instance-name

Lists the transports for the specified server instance.

# Examples

## Example 1 Listing Transports

The following command lists all the transports for the server instance:

```
asadmin> list-transports
http1-trans
tcp
Command list-transports executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-transport\(1\)](#), [delete-transport\(1\)](#)

# list-virtual-servers

Lists the existing virtual servers

## Synopsis

```
asadmin [asadmin-options] list-virtual-servers [--help]
[target]
```

## Description

The `list-virtual-servers` subcommand lists the existing virtual servers. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### target

Restricts the listing to virtual servers for a specified target. Valid values are as follows:

`server`

Lists the virtual servers for the default server instance. This is the default value.

### configuration-name

Lists the virtual servers for the specified configuration.

### cluster-name

Lists the virtual servers for all server instances in the specified cluster.

### instance-name

Lists the virtual servers for the specified server instance.

# Examples

## Example 1 Listing Virtual Servers

The following command lists all the virtual servers for the server instance:

```
asadmin> list-virtual-servers
server
__asadmin
Command list-virtual-servers executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-virtual-server\(1\)](#), [delete-virtual-server\(1\)](#)

# list-web-context-param

Lists servlet context-initialization parameters of a deployed web application or module

## Synopsis

```
asadmin [asadmin-options] list-web-context-param [--help]
[--name=context-param-name] application-name[/module]
```

## Description

The **list-web-context-param** subcommand lists the servlet context-initialization parameters of one of the following items:

- A deployed web application
- A web module in a deployed Java Platform, Enterprise Edition (Jakarta EE) application

The application must already be deployed. Otherwise, an error occurs.

The **list-web-context-param** subcommand lists only parameters that have previously been set by using the **set-web-context-param(1)** subcommand. The subcommand does not list parameters that are set only in the application's deployment descriptor.

For each parameter, the following information is displayed:

- The name of the parameter
- The value to which the parameter is set
- The value of the **--ignoreDescriptorItem** option of the **set-web-context-param** subcommand that was specified when the parameter was set
- The description of the parameter or **null** if no description was specified when the parameter was set

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the **asadmin(1M)** help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--name**

The name of the servlet context-initialization parameter that is to be listed. If this option is omitted, all parameters of the application that have previously been set are listed.

# Operands

**application-name**

The name of the application. This name can be obtained from the Administration Console or by using the [list-applications\(1\)](#) subcommand.

The application must already be deployed. Otherwise, an error occurs.

**module**

The relative path to the module within the application's enterprise archive (EAR) file. The path to the module is specified in the `module` element of the application's `application.xml` file.

`module` is required only if the servlet context-initialization parameter applies to a web module of a Jakarta EE application. If specified, `module` must follow `application-name`, separated by a slash (/).

For example, the `application.xml` file for the `myApp` application might specify the following web module:

```
<module>
  <web>
    <web-uri>myWebModule.war</web-uri>
  </web>
</module>
```

The module would be specified as the operand of this command as `myApp/myWebModule.war`.

# Examples

## Example 1 Listing Servlet Context-Initialization Parameters for a Web Application

This example lists all servlet context-initialization parameters of the web application `basic-ezcomp` that have been set by using the `set-web-context-param` subcommand. Because no description was specified when the `javax.faces.PROJECT_STAGE` parameter was set, `null` is displayed instead of a description for this parameter.

```
asadmin> list-web-context-param basic-ezcomp  
javax.faces.STATE_SAVING_METHOD = client ignoreDescriptorItem=false  
//The location where the application's state is preserved  
javax.faces.PROJECT_STAGE = null ignoreDescriptorItem=true //null
```

Command list-web-context-param executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [set-web-context-param\(1\)](#), [unset-web-context-param\(1\)](#)

# list-web-env-entry

Lists environment entries for a deployed web application or module

## Synopsis

```
asadmin [asadmin-options] list-web-env-entry [--help]
[--name=env-entry-name] application-name[/module]
```

## Description

The `list-web-env-entry` subcommand lists the environment entries for one of the following items:

- A deployed web application
- A web module in a deployed Java Platform, Enterprise Edition (Jakarta EE) application

The application must already be deployed. Otherwise, an error occurs.

The `list-web-env-entry` subcommand lists only entries that have previously been set by using the `set-web-env-entry(1)` subcommand. The subcommand does not list environment entries that are set only in the application's deployment descriptor.

For each entry, the following information is displayed:

- The name of the entry
- The Java type of the entry
- The value to which the entry is set
- The value of the `--ignoreDescriptorItem` option of the `set-web-env-entry` subcommand that was specified when the entry was set
- The description of the entry or `null` if no description was specified when the entry was set

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--name**

The name of the environment entry that is to be listed. The name is a JNDI name relative to the `java:comp/env` context. The name must be unique within a deployment component. If this option is omitted, all environment entries that have previously been set for the application are listed.

# Operands

## application-name

The name of the application. This name can be obtained from the Administration Console or by using the `list-applications(1)` subcommand.

The application must already be deployed. Otherwise, an error occurs.

## module

The relative path to the module within the application's enterprise archive (EAR) file. The path to the module is specified in the `module` element of the application's `application.xml` file.

module is required only if the environment entry applies to a web module of a Jakarta EE application. If specified, module must follow application-name, separated by a slash (/).

For example, the `application.xml` file for the `myApp` application might specify the following web module:

```
<module>
  <web>
    <web-uri>myWebModule.war</web-uri>
  </web>
</module>
```

:: The module would be specified as the operand of this command as `myApp/myWebModule.war`.

# Examples

## Example 1 Listing Environment Entries for a Web Application

This example lists all environment entries that have been set for the web application `hello` by using the `set-web-env-entry` subcommand. Because no description was specified when the `Hello Port` environment entry was set, `null` is displayed instead of a description for this entry.

```
asadmin> list-web-env-entry hello
Hello User (java.lang.String) = techscribe ignoreDescriptorItem=false
//User authentication for Hello application
Hello Port (java.lang.Integer) = null ignoreDescriptorItem=true //null

Command list-web-env-entry executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [set-web-env-entry\(1\)](#), [unset-web-env-entry\(1\)](#)

# login

Logs you into a domain

## Synopsis

```
asadmin [asadmin-options] login [--help]
```

## Description

The purpose of the `login` subcommand is to ease domain administration by letting you log into a particular domain. If Eclipse GlassFish domains are created on various machines (locally), you can run the `asadmin` utility from any of these machines and manage domains located elsewhere (remotely). This is especially useful when a particular machine is chosen as an administration client that manages multiple domains and servers.

The `login` subcommand prompts you for the administrator user name and password. After successful login, the `.asadminpass` file is created in your home directory. (This is the same file that is modified when you run the `create-domain` subcommand with the `--savelogin` option.) The literal host name is stored, and no resolution with the DNS is attempted. If a domain is being administered from other machines, it is sufficient to run the `login` subcommand once. You do not need to specify the `asadmin` utility options `--user` and `--passwordfile` when you run additional remote subcommands on that domain. After you have logged into a domain, you still need to provide the host and port for any subsequent remote subcommands unless you chose the default values for `--host` (localhost) and `--port` (4848) options.

Subsequent use of same subcommand with the same parameters will result in overwriting the contents of the `.asadminpass` file for the given administration host and port. You can decide to overwrite the file or to reject such a login.

Login information is saved permanently and can be used across multiple domain restarts.

There is no `logout` subcommand. If you want to log in to another domain, run the `login` subcommand and specify new values for the `asadmin` utility options `--host` and `--port`.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

--help

-?

Displays the help text for the subcommand.

## Examples

### Example 1 Logging Into a Domain on a Remote Machine

This example logs into a domain located on another machine. Options are specified before the `login` subcommand.

```
asadmin --host foo --port 8282 login
Please enter the admin user name>admin
Please enter the admin password>

Trying to authenticate for administration of server at host [foo]
and port [8282] ...
Login information relevant to admin user name [admin] for host [foo]
and admin port [8282] stored at [/.asadminpass] successfully.
Make sure that this file remains protected. Information stored in this
file will be used by asadmin commands to manage associated domain.
```

### Example 2 Logging Into a Domain on the Default Port of Localhost

This example logs into a domain on `myhost` on the default port. Options are specified before the `login` subcommand.

```
asadmin --host myhost login
Please enter the admin user name>admin
Please enter the admin password>
Trying to authenticate for administration of server
at host [myhost] and port [4848] ...
An entry for login exists for host [myhost] and port [4848], probably
from an earlier login operation.
Do you want to overwrite this entry (y/n)?y
Login information relevant to admin user name [admin] for host [myhost]
and admin port [4848] stored at [/home/joe/.asadminpass] successfully.
Make sure that this file remains protected. Information stored in this
file will be used by asadmin commands to manage associated domain.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-domain\(1\)](#), [delete-domain\(1\)](#)

# migrate-timers

Moves EJB timers when a clustered instance was stopped or has crashed

## Synopsis

```
asadmin [asadmin-options] migrate-timers [--help]
[--target target_server_name]
server_name
```

## Description

The **migrate-timers** subcommand moves EJB timers to a specified server when a server instance stops or crashes, if automatic timer migration is not enabled in the cluster configuration. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This is the target server instance. If this option is not specified, then DAS will find a server instance or multiple server instances. A migration notification will be sent to the selected server instances.

**--destination**

This option is deprecated. It works exactly as the **--target** option does.

## Operands

### server\_name

This is the server instance on which the timers are currently located. This server instance should not be running during the migration process.

# Examples

## Example 1 Migrating Timers

This example shows how to migrate timers from the server named `instance1` to a server named `instance2`.

```
asadmin>migrate-timers --target instance2 instance1
This command was successfully executed.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-timers\(1\)](#)

The script content on this page is for navigation purposes only and does not alter the content in any way.

# monitor

Displays monitoring data for commonly used components and services

## Synopsis

```
asadmin [asadmin-options] monitor [--help]
--type type
[--filename filename]
[--interval interval]
[--filter filter]
instance-name
```

## Description

The **monitor** subcommand displays statistics for commonly monitored Eclipse GlassFish components and services. The **--type** option must be used to specify the object for which statistics are to be displayed. Data is displayed continuously in a tabular form, or the data can be displayed at a particular time interval by using the **--interval** option.

Before a given component or service can be monitored, monitoring must be enabled (set to HIGH or LOW) for the component or service by using the Administration Console, the enable-monitoring subcommand, or the set subcommand.

The monitor subcommand has options for filtering the results and capturing the output in a Comma Separated Values (CSV) file. The output appears in a table format. To view the legend of the table header, type **h**.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--type**

The component or service to monitor. This option is required. No default value is defined.

**httpListener**

For this type, the attribute `server.monitoring-service.module-monitoring-levels.http-service` must be set to LOW or HIGH.

Displays the following statistics for the HTTP listener service:

**ec**

The total number errors in the processing of HTTP requests.

**mt**

The longest response time (in milliseconds) for the processing of a single HTTP request.

**pt**

The total amount of time (in milliseconds) that the HTTP listener service has spent in processing HTTP requests.

**rc**

The total number of requests that the HTTP listener service has processed.

**jvm**

For this type, the attribute `server.server-config.monitoring-service.module-monitoring-levels.jvm` must be set to LOW or HIGH.

Displays the following statistics for the Virtual Machine for the Java platform (Java Virtual Machine or JVM machine):<sup>Footnote 1</sup>

**UpTime**

The number of milliseconds that the JVM machine has been running since it was last started.

**min**

The initial amount of memory (in bytes) that the JVM machine requests from the operating system for memory management during startup.

**max**

The maximum amount of memory that can be used for memory management.

**low**

Retained for compatibility with other releases.

**high**

Retained for compatibility with other releases.

**count**

The amount of memory (in bytes) that is guaranteed to be available for use by the JVM machine.

**webmodule**

For this type, the attribute `server.server-config.monitoring-service.module-monitoring-levels.web-container` must be set to LOW or HIGH.

Displays the following statistics for all deployed web modules:

**asc**

The number of currently active sessions.

**ast**

The total number of sessions that are currently active or have been active previously.

**rst**

The total number of rejected sessions.

**st**

The total number of sessions that have been created.

**ajlc**

The number of currently active JavaServer Pages ( JSP) technology pages that are loaded.

**mjlc**

The maximum number of JSP technology pages that were active at any time simultaneously.

**tjlc**

Total number of JSP technology pages that have been loaded.

**aslc**

The number of currently active Java servlets that are loaded.

**mslc**

The maximum number of Java servlets that were active at any time simultaneously.

**tslc**

The total number of Java servlets that have been loaded.

**--filename**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--interval**

The interval in seconds before capturing monitoring attributes. The interval must be greater than 0. The monitoring attributes are displayed on `stdout` until you type Control-C or `q`. The default value is 30.

**--filter**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

**instance-name**

The server instance for which to view monitoring data. The default value is [server](#).

## Examples

### Example 1 Displaying Monitoring Statistics by Interval

This example displays monitoring data for the JVM machine every 2000 seconds.

```
asadmin> monitor --type=jvm --interval 2000 server
          JVM Monitoring
UpTime(ms)           Heap and NonHeap Memory(bytes)
current               min        max       low      high      count
957843              29523968  188284928  0         0       60370944
q
Command monitor executed successfully.
```

### Example 2 Filtering the Monitoring Data

This example uses the filter option to show [http-listener-1](#) statistics.

```
asadmin> monitor --type httplistener --filter http-listener-1 server
          HTTP Listener Monitoring: http-listener-1
br   bs   c200 c2xx c302 c304 c3xx c400 c401 c403 c404 c4xx c503 c5xx coc  co
ctc  ctb  ec   moc  mst   mt    mtm  mst   pt    rc
0     0    0    0    0    3    3    0    0    0    0    0    0    0    0
2     0    0    1    20   20   2    2    6    3
```

To see the legend for the table headings, type [h](#).

```
*****
*
* br   = Cumulative value of the Bytes received by each of the Request Processors
*
* bs   = Cumulative value of the Bytes sent by each of the Request Processors
*
* c200 = Number of responses with a status code equal to 200
*
* c2xx = Number of responses with a status code in the 2xx range
*
* c302 = Number of responses with a status code equal to 302
*
* c304 = Number of responses with a status code equal to 304
*
* c3xx = Number of responses with a status code in the 3xx range
*
* c400 = Number of responses with a status code equal to 400
*
* c401 = Number of responses with a status code equal to 401
*
* c403 = Number of responses with a status code equal to 403
*
* c404 = Number of responses with a status code equal to 404
*
* c4xx = Number of responses with a status code equal to 4xx
*
* c504 = Number of responses with a status code equal to 504
*
* c5xx = Number of responses with a status code in the 5xx range
*
* coc  = Number of open connections
*
* co   = Number of responses with a status code outside the 2xx, 3xx, 4xx, and 5xx range
*
* ctc  = Number of request processing threads currently in the listener thread pool
*
* ctb  = Number of request processing threads currently in use in the listener thread
*
*       pool serving requests
*
* ec   = Number of responses with a status code equal to 400
*
* moc  = Maximum number of open connections
*
* mst  = Minimum number of request processing threads that will be created at listener
*
*       startup time and maintained as spare threads above the current thread count
*
```

```
* mt    = Maximum number of request processing threads that are created by the listener
*
* mtm   = Provides the longest response time for a request - not a cumulative value, but
*
*          the largest response time from among the response times
*
* pt    = Cumulative value of the times taken to process each request. The processing
*
*          time is the average of request processing times over the request count
*
* rc    = Cumulative number of the requests processed so far
*
*****
*
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[enable-monitoring\(1\)](#), [disable-monitoring\(1\)](#), [set\(1\)](#)

[monitoring\(5ASC\)](#)

"[Administering the Monitoring Service](#)" in Eclipse GlassFish Administration Guide

## Footnote Legend

Footnote 1: The terms "Java Virtual Machine" and "JVM" mean a Virtual Machine for the Java platform.

# multimode

Allows multiple subcommands to be run while preserving environment settings and remaining in the `asadmin` utility

## Synopsis

```
asadmin [asadmin-options] multimode [--help]
[--file filename]
[--printprompt={true|false}] [--encoding encode]
```

## Description

The `multimode` subcommand processes `asadmin` subcommands sequentially in a single session. The command-line interface prompts for a subcommand, runs that subcommand, displays the results of that subcommand, and then prompts for the next subcommand. All the `asadmin` options set in `multimode` apply to subsequent commands until the `multimode` session is exited. You exit `multimode` by typing `exit`, `quit`, or Ctrl-D.

You can use the `export` subcommand to set your environment, or use the `unset` subcommand to remove environment variables from the `multimode` environment.

You can also provide subcommands by passing a previously prepared list of subcommands from a file or standard input (pipe). When you use a file, you can include comment lines in the file by entering the hash symbol (#) as the first character of the line.

You can invoke `multimode` from within a `multimode` session. When you exit the second `multimode` environment, you return to your original `multimode` environment.

All the remote `asadmin` utility options can be supplied when invoking the `multimode` subcommand. The settings will apply as defaults for all subcommands that are run within the `multimode` session. For a list of the `asadmin` utility options, see the [asadmin\(1M\)](#) help page.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--file****-f**

Reads the subcommands in the specified file.

**--printprompt**

Controls printing of the `asadmin` prompt. By default, this option is set to the same value as the `--interactive` `asadmin` utility option. Normally you will not need to specify this option. Default is true.

**--encoding**

Specifies the character set for the file to be decoded. By default, the system character set is used.

## Examples

### Example 1 Starting a Multimode Session

This example starts a multimode session where: % is the system prompt.

```
% asadmin multimode  
asadmin>
```

You can also start a multimode session by typing `asadmin` without options or subcommands at the system prompt.

### Example 2 Running Multiple Commands From a File

This example runs a sequence of subcommands from the `commands_file.txt` file.

```
% asadmin multimode --file commands_file.txt
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[export\(1\)](#), [unset\(1\)](#)

# osgi

Delegates the command line to the Apache Felix Gogo remote shell for the execution of OSGi shell commands

## Synopsis

```
asadmin [asadmin-options] osgi [--help]
[--session session]
[--session-id session-id]
[--instance instance]
[command_line]
```

## Description

The `osgi` subcommand delegates the command line to the Apache Felix Gogo remote shell for the execution of OSGi shell commands. Commands are executed by the remote shell and results are returned by the `asadmin` utility. The remote shell is provided with Eclipse GlassFish and used to administer and inspect the OSGi runtime.

Multiple command-line sessions can be created. Use the `--session` and `--session-id` options to run commands in a specific command-line session. If no session is specified, a new session is created to run commands and closed when execution completes.

A related subcommand is the `osgi-shell` subcommand, which enables you to run multiple commands from a file or run commands interactively. For more information about the `osgi-shell` subcommand, see the [osgi-shell\(1\)](#) help page.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the `osgi` subcommand.

`--session`

Performs command-line session operations. Valid values are:

**new**

Creates a new session and returns a session ID.

**stop**

Stops the session with the specified session ID.

**list**

Lists all active sessions.

**execute**

Runs a command in the session with the specified session ID.

**--session-id**

Specifies the session ID for command-line session operations.

**--instance**

Specifies the server instance to which the command is being delegated.

The default is the domain administration server (DAS). The DAS must be running to run a command on another instance.

# Operands

**command\_line**

The complete command-line syntax as provided for commands in the Apache Felix Gogo remote shell.

# Examples

## Example 1 Listing Apache Felix Gogo Remote Shell Commands

This example lists the Apache Felix Gogo remote shell commands that can be used with the `osgi` subcommand.

Some lines of output are omitted from this example for readability.

```
asadmin> osgi help
felix:bundlelevel
felix:cd
felix:frameworklevel
felix:headers
felix:help
felix:inspect
felix:install
felix:lb
felix:log
felix:ls
felix:refresh
felix:resolve
...
gogo:cat
gogo:each
gogo:echo
gogo:format
gogo:getopt
gogo:gosh
gogo:grep
...
Command osgi executed successfully.
```

## Example 2 Running a Remote Shell Command

This example runs the Felix Remote Shell Command `lb` without any arguments to list all installed OSGi bundles.

Some lines of output are omitted from this example for readability.

```
asadmin> osgi lb
START LEVEL 2
ID|State      |Level|Name
0|Active     | 0|System Bundle
1|Active     | 1|Metro Web Services API OSGi Bundle
2|Active     | 1|jakarta.annotation API
3|Active     | 1|jaxb-api
...
Command osgi executed successfully.
```

## Example 3 Running Commands That Create and Target a Specific Command-Line Session

This example runs commands that create and target a specific command-line session.

Some lines of output are omitted from this example for readability.

```
asadmin> osgi --session new  
9537e570-0def-4f2e-9c19-bc8f51a8082f  
...  
asadmin> osgi --session list  
9537e570-0def-4f2e-9c19-bc8f51a8082f  
...  
asadmin> osgi --session execute --session-id 9537e570-0def-4f2e-9c19-bc8f51a8082f lb  
START LEVEL 2  
ID|State      |Level|Name  
0|Active      | 0|System Bundle  
1|Active      | 1|Metro Web Services API OSGi Bundle  
2|Active      | 1|jakarta.annotation API  
3|Active      | 1|jaxb-api  
...  
asadmin> osgi --session stop --session-id 9537e570-0def-4f2e-9c19-bc8f51a8082f  
Command osgi executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[osgi-shell\(1\)](#)

# osgi-shell

Provides interactive access to the Apache Felix Gogo remote shell for the execution of OSGi shell commands

## Synopsis

```
asadmin [asadmin-options] osgi-shell [--help]
[--file file]
[--printprompt={false|true}]
[--encoding encoding]
```

## Description

The [osgi-shell](#) subcommand provides interactive access to the Apache Felix Gogo remote shell for the execution of OSGi shell commands. The remote shell is provided with Eclipse GlassFish and used to administer and inspect the OSGi runtime.

OSGi shell commands are executed on the server and results are printed on the client. Because the shell is interactive, no operands are accepted. Scripting is supported, which means that multiple commands can be executed in sequence from a text file.

A related subcommand is the [osgi](#) subcommand, which passes a single command to the remote shell for execution. Results are returned by the [asadmin](#) utility. For more information about the [osgi](#) subcommand, see the [osgi\(1\)](#) help page.

This subcommand is supported in local mode only. Unlike other local subcommands, however, the domain administration server (DAS) and the server instance whose shell is being accessed must be running.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

[--help](#)

[-?](#)

Displays the help text for the subcommand.

[--file](#)

[-f](#)

Reads the commands in the specified file.

**--printprompt**

Controls printing of the shell prompt. The default value is `true`, which means the shell prompt is displayed.

**--encoding**

Specifies the character set for the file to be decoded. By default, the system character set is used.

## Examples

### Example 1 Listing Apache Felix Gogo Remote Shell Commands

This example lists Apache Felix Gogo remote shell commands.

Some lines of output are omitted from this example for readability.

```
asadmin> osgi-shell
Use "exit" to exit and "help" for online help.
gogo$ help
felix:bundlelevel
felix:cd
felix:frameworklevel
felix:headers
felix:help
felix:inspect
felix:install
felix:lb
felix:log
felix:ls
...
gogo:cat
gogo:each
gogo:echo
gogo:format
gogo:getopt
gogo:gosh
gogo:grep
...
gogo$
```

## Example 2 Running a Remote Shell Command

This example runs the Felix Remote Shell Command `lb` without any arguments to list all installed OSGi bundles.

Some lines of output are omitted from this example for readability.

```
asadmin> osgi-shell
Use "exit" to exit and "help" for online help.
gogo$ lb
START LEVEL 2
ID|State      |Level|Name
0|Active      | 0|System Bundle
1|Active      | 1|Metro Web Services API OSGi Bundle
2|Active      | 1|jakarta.annotation API
3|Active      | 1|jaxb-api
...
gogo$
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[osgi\(1\)](#)

# ping-connection-pool

Tests if a connection pool is usable

## Synopsis

```
asadmin [asadmin-options] ping-connection-pool [--help]
pool_name
[--appname application [--modulename module]]
```

## Description

The **ping-connection-pool** subcommand tests if an existing JDBC or connector connection pool is usable. For example, if you create a new JDBC connection pool for an application that is expected to be deployed later, the JDBC pool is tested with this subcommand before deploying the application.

Before testing availability of a connection pool, you must create the connection pool with authentication and ensure that the server or database is started.

This subcommand is supported in remote mode only.

### Application Scoped Resources

The **ping-connection-pool** subcommand can target resources that are scoped to a specific application or module, as defined in the **glassfish-resources.xml** for the GlassFish domain.

- To reference the **jndi-name** for an application scoped resource, perform the lookup using the **java:app** prefix.
- To reference the **jndi-name** for a module scoped resource, perform the lookup using the **java:module** prefix.

The **jndi-name** for application-scoped-resources or module-scoped-resources are specified using the format **java:app/jdbc/myDataSource** or **java:module/jdbc/myModuleLevelDataSource**. This naming scope is defined in the Jakarta EE 6 Specification (<http://download.oracle.com/javaee/6/api/>).

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--appname**

Name of the application in which the application scoped resource is defined.

**--modulename**

Name of the module in which the module scoped resource is defined.

## Operands

**pool\_name**

Name of the connection pool to be reinitialized.

## Examples

### Example 1 Contacting a Connection Pool

This example tests to see if the connection pool named **DerbyPool** is usable.

```
asadmin> ping-connection-pool DerbyPool
Command ping-connection-pool executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-connection-pool\(1\)](#), [create-jdbc-connection-pool\(1\)](#), [delete-connector-connection-pool\(1\)](#), [delete-jdbc-connection-pool\(1\)](#), [list-connector-connection-pools\(1\)](#), [list-jdbc-connection-pools\(1\)](#)



# ping-node-dcom

Tests if a node that is enabled for communication over DCOM is usable

## Synopsis

```
asadmin [asadmin-options] ping-node-dcom [--help]
[--validate={false|true}] node-name
```

## Description

The **ping-node-dcom** subcommand tests if a node that is enabled for communication over the Distributed Component Object Model (DCOM) remote protocol is usable. The DCOM protocol is available only on Windows systems. This subcommand requires DCOM to be configured on the machine where the domain administration server (DAS) is running and on the machine where the node resides. You may run this command from any machine that can contact the DAS.

If the node is usable, the subcommand displays a confirmation that the subcommand could connect to the node through DCOM. This confirmation includes the name of the host that the node represents.

Optionally, the subcommand can also validate the node to determine if the [asadmin\(1M\)](#) utility can run on the host that the node represents. To validate a node, the subcommand runs the [version\(1\)](#) subcommand. If the node is valid, the subcommand displays the version that the [version](#) subcommand returns.

The node that is specified as the operand of this subcommand must be enabled for communication over DCOM. If the node is not enabled for communication over DCOM, an error occurs. To determine whether a node is enabled for communication over DCOM, use the [list-nodes\(1\)](#) subcommand.



To test whether a node that is enabled for communication over secure shell (SSH) is usable, use the [ping-node-ssh\(1\)](#) subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--validate**

Specifies whether the subcommand validates the node. Possible values are as follows:

**true**

The node is validated.

**false**

The node is not validated (default).

## Operands

### node-name

The name of the node to test. The node must be enabled for communication over DCOM. Otherwise, an error occurs.

## Examples

### Example 1 Testing if a DCOM-Enabled Node Is Usable

This example tests if the DCOM-enabled node `wpmd2` is usable.

```
asadmin> ping-node-dcom wpmd2
Successfully made DCOM connection to node wpmd2 (wpmd2.example.com)
Command ping-node-dcom executed successfully.
```

### Example 2 Validating a DCOM-Enabled Node

This example validates the DCOM-enabled node `adc-node`.

```
asadmin> ping-node-dcom --validate=true adc-node
Successfully made DCOM connection to node adc-node (adc-node.example.com)
GlassFish version found at C:\glassfish7:
Using locally retrieved version string from version class.
Version = Eclipse GlassFish 7.0.0 (build 18)
Command version executed successfully.
Command ping-node-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-dcom\(1\)](#), [delete-node-dcom\(1\)](#), [list-nodes\(1\)](#), [ping-node-ssh\(1\)](#), [update-node-dcom\(1\)](#), [validate-dcom\(1\)](#), [version\(1\)](#)

# ping-node-ssh

Tests if a node that is enabled for communication over SSH is usable

## Synopsis

```
asadmin [asadmin-options] ping-node-ssh [--help]
[--validate={false|true}] node-name
```

## Description

The [ping-node-ssh](#) subcommand tests if a node that is enabled for communication over secure shell (SSH) is usable. This subcommand requires secure shell (SSH) to be configured on the machine where the domain administration server (DAS) is running and on the machine where the node resides. You may run this command from any machine that can contact the DAS.

If the node is usable, the subcommand displays a confirmation that the subcommand could connect to the node through SSH. This confirmation includes the name of the host that the node represents.

Optionally, the subcommand can also validate the node to determine if the [asadmin\(1M\)](#) utility can run on the host that the node represents. To validate a node, the subcommand runs the [version\(1\)](#) subcommand. If the node is valid, the subcommand displays the version that the [version](#) subcommand returns.

The node that is specified as the operand of this subcommand must be enabled for communication over SSH. If the node is not enabled for communication over SSH, an error occurs. To determine whether a node is enabled for communication over SSH, use the [list-nodes\(1\)](#) subcommand.



To test whether a node that is enabled for communication over the Distributed Component Object Model (DCOM) remote protocol is usable, use the [ping-node-dcom\(1\)](#) subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

[--help](#)

[-?](#)

Displays the help text for the subcommand.

**--validate**

Specifies whether the subcommand validates the node. Possible values are as follows:

**true**

The node is validated.

**false**

The node is not validated (default).

## Operands

### node-name

The name of the node to test. The node must be enabled for communication over SSH. Otherwise, an error occurs.

## Examples

### Example 1 Testing if an SSH-Enabled Node Is Usable

This example tests if the SSH-enabled node **sj03-node** is usable.

```
asadmin> ping-node-ssh sj03-node
Successfully made SSH connection to node sj03-node (sj03.example.com)
Command ping-node-ssh executed successfully.
```

### Example 2 Validating an SSH-Enabled Node

This example validates the SSH-enabled node **adc-node**.

```
asadmin> ping-node-ssh --validate=true adc-node
Successfully made SSH connection to node adcnode (adc.example.com)
GlassFish version found at /export/glassfish7:
Using locally retrieved version string from version class.
Version = Eclipse GlassFish 7.0.0 (build 2021-12-10T19:08:14+0100)
Command version executed successfully.
Command ping-node-ssh executed successfully.
```

---

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-ssh\(1\)](#), [delete-node-ssh\(1\)](#), [list-nodes\(1\)](#), [ping-node-dcom\(1\)](#), [setup-ssh\(1\)](#), [update-node-ssh\(1\)](#), [version\(1\)](#)

# recover-transactions

Manually recovers pending transactions

## Synopsis

```
asadmin [asadmin-options] recover-transactions [--help]
[--transactionlogdir transaction_log_dir]
[--target target_server_name] server_name
```

## Description

The **recover-transactions** subcommand manually recovers pending transactions.

For an installation of multiple server instances, you can run the **recover-transactions** subcommand from a surviving server instance to recover transactions after a server failure. To use this subcommand in this way, the following conditions must be met:

- Delegated transaction recovery is disabled.
- Transaction logs are stored on a shared file system or in a database that is accessible to all server instances.

For a stand-alone server, do not use this subcommand to recover transactions after a server failure. For a stand-alone server, the **recover-transactions** subcommand can recover transactions only when a resource fails, but the server is still running. If a stand-alone server fails, only the full startup recovery process can recover transactions that were pending when the server failed.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--transactionlogdir**

The location of the transaction logs for a server for which transaction recovery is requested. This option applies only if transaction logs are stored on a shared file system.

**--target**

The target server that performs the recovery for the server that is specified by the `server_name` operand. The target server should be running.

**--destination**

This option is deprecated. It works exactly as the `--target` option does.

# Operands

**server\_name**

For a stand-alone server, the value of this operand is typically `server`. Transactions are recovered only if a resource fails, but the server is still running.

For an installation of multiple server instances, the value of this operand is the name of the server for which the recovery is required. The in-flight transactions on this server will be recovered. If this server is running, recovery is performed by the same server. In this situation, the `--transactionlogdir` and `--target` options should be omitted. If the server is not running, the `--target` option is required, and the `--transactionlogdir` option is also required if transaction logs are stored on a shared file system.

## Examples

### Example 1 Recovering transactions on a running server

```
% asadmin recover-transactions server1  
Transaction recovered.
```

### Example 2 Recovering transactions for a server that is not running

```
% asadmin recover-transactions --transactionlogdir /logs/tx --target server1 server2  
Transaction recovered.
```

## Exit Status

**0**

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[freeze-transaction-service\(1\)](#), [rollback-transaction\(1\)](#), [unfreeze-transaction-service\(1\)](#)

"[Administering Transactions](#)" in Eclipse GlassFish Administration Guide

"[Transactions](#)" in The Jakarta EE Tutorial

# redeploy

Redeploys the specified component

## Synopsis

```
asadmin [asadmin-options] redeploy [--help]
--name component_name
[--upload={true|false}]
[--retrieve local_dirpath]
[--dbvendorname dbvendorname]
[--createtables={true|false}|--dropandcreatetables={true|false}]
[--uniquetablenames={true|false}]
[--deploymentplan deployment_plan]
[--altdd alternate_deploymentdescriptor]
[--runtimealtdd runtime_alternate_deploymentdescriptor]
[--deploymentorder deployment_order]
[--enabled={true|false}]
[--generateremistubs={false|true}]
[--contextroot context_root]
[--precompilejsp={true|false}]
[--verify={false|true}]
[--virtualservers virtual_servers]
[--availabilityenabled={false|true}]
[--asyncreplication={true|false}]
[--lbenabled={true|false}]
[--keepstate={false|true}]
[--libraries jar_file[,jar_file]*]
[--target target]
[--type pkg-type]
[--properties(name=value)[:name=value]*]
[file_archive|filepath]
```

## Description

The `redeploy` subcommand redeploys an enterprise application, web application, module based on the Enterprise JavaBeans (EJB) specification (EJB module), connector module, or application client module that is already deployed or already exists. The `redeploy` subcommand preserves the settings and other options with which the application was originally deployed. The application must already be deployed. Otherwise, an error occurs.

This subcommand is supported in remote mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

-?

Displays the help text for the subcommand.

### --virtualservers

One or more virtual server IDs. Multiple IDs are separated by commas.

### --contextroot

Valid only if the archive is a web module. It is ignored for other archive types; it will be the value specified by default-context-path in web.xml, if specified; defaults to filename without extension.

### --precompilejsp

By default this option does not allow the JSP to be precompiled during deployment. Instead, JSPs are compiled during runtime. Default is `false`.

### --verify

If set to true and the required verifier packages are installed from the Update Tool, the syntax and semantics of the deployment descriptor is verified. Default is `false`.

### --name

Name of the deployable component.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. For more information about module and application versions, see "Module and Application Versions" in Eclipse GlassFish Application Deployment Guide.

### --upload

Specifies whether the subcommand uploads the file to the DAS. In most situations, this option can be omitted. Valid values are as follows:

#### `false`

The subcommand does not upload the file and attempts to access the file through the specified file name. If the DAS cannot access the file, the subcommand fails.

For example, the DAS might be running as a different user than the administration user and does not have read access to the file. In this situation, the subcommand fails if the `--upload` option is `false`.

**true**

The subcommand uploads the file to the DAS over the network connection.

The default value depends on whether the DAS is on the host where the subcommand is run or is on a remote host.

- If the DAS is on the host where the subcommand is run, the default is **false**.
- If the DAS is on a remote host, the default is **true**.

If a directory filepath is specified, this option is ignored.

**--retrieve**

Retrieves the client stub JAR file from the server machine to the local directory.

**--dbvendorname**

Specifies the name of the database vendor for which tables are created. Supported values include `db2`, `mssql`, `oracle`, `derby`, `javadb`, `postgresql`, and `sybase`, case-insensitive. If not specified, the value of the `database-vendor-name` attribute in `glassfish-ejb-jar.xml` is used. If no value is specified, a connection is made to the resource specified by the `jndi-name` subelement of the `cmp-resource` element in the `glassfish-ejb-jar.xml` file, and the database vendor name is read. If the connection cannot be established, or if the value is not recognized, SQL-92 compliance is presumed.

**--createtables**

If specified as true, creates tables at deployment of an application with unmapped CMP beans. If specified as false, tables are not created. If not specified, the value of the `create-tables-at-deploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file determines whether or not tables are created. No unique constraints are created for the tables.

**--dropandcreatetables**

If specified as true when the component is redeployed, the tables created by the previous deployment are dropped before creating the new tables. Applies to deployed applications with unmapped CMP beans. If specified as false, tables are neither dropped nor created. If not specified, the tables are dropped if the `drop-tables-at-undeploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file is set to true, and the new tables are created if the `create-tables-at-deploy` entry in the `cmp-resource` element of the `glassfish-ejb-jar.xml` file is set to true.

**--uniquetablename**

Guarantees unique table names for all the beans and results in a hash code added to the table names. This is useful if you have an application with case-sensitive bean names. Applies to applications with unmapped CMP beans.

**--deploymentplan**

Deploys the deployment plan, which is a JAR file that contains Eclipse GlassFish descriptors. Specify this option when deploying a pure EAR file. A pure EAR file is an EAR without Eclipse GlassFish descriptors.

**--altdd**

Deploys the application using a Jakarta EE standard deployment descriptor that resides outside of the application archive. Specify an absolute path or a relative path to the alternate deployment descriptor file. The alternate deployment descriptor overrides the top-level deployment descriptor packaged in the archive. For example, for an EAR, the `--altdd` option overrides `application.xml`. For a standalone module, the `--altdd` option overrides the top-level module descriptor such as `web.xml`.

**--runtimealtdd**

Deploys the application using a Eclipse GlassFish runtime deployment descriptor that resides outside of the application archive. Specify an absolute path or a relative path to the alternate deployment descriptor file. The alternate deployment descriptor overrides the top-level deployment descriptor packaged in the archive. For example, for an EAR, the `--runtimealtdd` option overrides `glassfish-application.xml`. For a standalone module, the `--runtimealtdd` option overrides the top-level module descriptor such as `glassfish-web.xml`. Applies to Eclipse GlassFish deployment descriptors only (`glassfish-*.xml`); the name of the alternate deployment descriptor file must begin with `glassfish-`. Does not apply to `sun-*.xml` deployment descriptors, which are deprecated.

**--deploymentorder**

Specifies the deployment order of the application. This is useful if the application has dependencies and must be loaded in a certain order at server startup. The deployment order is specified as an integer. The default value is 100. Applications with lower numbers are loaded before applications with higher numbers. For example, an application with a deployment order of 102 is loaded before an application with a deployment order of 110. If a deployment order is not specified, the default value of 100 is assigned. If two applications have the same deployment order, the first application to be deployed is the first application to be loaded at server startup.

The deployment order is typically specified when the application is first deployed but can also be specified or changed after initial deployment using the `set` subcommand. You can view the deployment order of an application using the `get` subcommand.

**--enabled**

Allows users to access the application. If set to `false`, users will not be able to access the application. This option enables the application on the specified target instance or cluster. If you deploy to the target `domain`, this option is ignored, since deploying to the domain doesn't deploy to a specific instance or cluster. The default is `true`.

**--generatermi stubs**

If set to `true`, static RMI-IIOP stubs are generated and put into the `client.jar`. If set to `false`, the stubs are not generated. Default is `false`.

**--availabilityenabled**

This option controls whether high-availability is enabled for web sessions and for stateful session bean (SFSB) checkpointing and potentially passivation. If set to false (default) all web session saving and SFSB checkpointing is disabled for the specified application, web application, or EJB module. If set to true, the specified application or module is enabled for high-availability. Set this option to true

only if high availability is configured and enabled at higher levels, such as the server and container levels.

#### --asyncreplication

This option controls whether web session and SFSB states for which high availability is enabled are first buffered and then replicated using a separate asynchronous thread. If set to true (default), performance is improved but availability is reduced. If the instance where states are buffered but not yet replicated fails, the states are lost. If set to false, performance is reduced but availability is guaranteed. States are not buffered but immediately transmitted to other instances in the cluster.

#### --lbenabled

This option controls whether the deployed application is available for load balancing. The default is true.

#### --keepstate

This option controls whether web sessions, SFSB instances, and persistently created EJB timers are retained between redeployments.

The default is false. This option is supported only on the default server instance, named `server`. It is not supported and ignored for any other target.

Some changes to an application between redeployments prevent this feature from working properly. For example, do not change the set of instance variables in the SFSB bean class.

For web applications, this feature is applicable only if in the `glassfish-web-app.xml` file the `persistence-type` attribute of the `session-manager` element is `file`.

For stateful session bean instances, the persistence type without high availability is set in the server (the `sfsb-persistence-type` attribute) and must be set to `file`, which is the default and recommended value.

If any active web session, SFSB instance, or EJB timer fails to be preserved or restored, none of these will be available when the redeployment is complete. However, the redeployment continues and a warning is logged.

To preserve active state data, Eclipse GlassFish serializes the data and saves it in memory. To restore the data, the class loader of the newly redeployed application deserializes the data that was previously saved.

#### --libraries

A comma-separated list of library JAR files. Specify the library JAR files by their relative or absolute paths. Specify relative paths relative to domain-dir`/lib/applibs`. The libraries are made available to the application in the order specified.

#### --target

Specifies the target to which you are deploying. Valid values are:

##### `server`

Deploys the component to the default server instance `server` and is the default value.

**domain**

Deploys the component to the domain. If **domain** is the target for an initial deployment, the application is deployed to the domain, but no server instances or clusters reference the application. If **domain** is the target for a redeployment, and dynamic reconfiguration is enabled for the clusters or server instances that reference the application, the referencing clusters or server instances automatically get the new version of the application. If redeploying, and dynamic configuration is disabled, the referencing clusters or server instances do not get the new version of the application until the clustered or standalone server instances are restarted.

**cluster\_name**

Deploys the component to every server instance in the cluster.

**instance\_name**

Deploys the component to a particular stand-alone server instance.

**--type**

The packaging archive type of the component that is being deployed. Possible values are as follows:

**car**

The component is packaged as a CAR file.

**ear**

The component is packaged as an EAR file.

**ejb**

The component is an EJB packaged as a JAR file.

**osgi**

The component is packaged as an OSGi bundle.

**rar**

The component is packaged as a RAR file.

**war**

The component is packaged as a WAR file.

**--properties or --property**

Optional keyword-value pairs that specify additional properties for the deployment. The available properties are determined by the implementation of the component that is being deployed or redeployed. The **--properties** option and the **--property** option are equivalent. You can use either option regardless of the number of properties that you specify.

You can specify the following properties for a deployment:

**jar-signing-alias**

Specifies the alias for the security certificate with which the application client container JAR file

is signed. Java Web Start will not run code that requires elevated permissions unless it resides in a JAR file signed with a certificate that the user's system trusts. For your convenience, Eclipse GlassFish signs the JAR file automatically using the certificate with this alias from the domain's keystore. Java Web Start then asks the user whether to trust the code and displays the Eclipse GlassFish certificate information. To sign this JAR file with a different certificate, add the certificate to the domain keystore, then use this property. For example, you can use a certificate from a trusted authority, which avoids the Java Web Start prompt, or from your own company, which users know they can trust. Default is `s1as`, the alias for the self-signed certificate created for every domain.

#### **java-web-start-enabled**

Specifies whether Java Web Start access is permitted for an application client module. Default is true.

#### **compatibility**

Specifies the Eclipse GlassFish release with which to be backward compatible in terms of JAR visibility requirements for applications. The only allowed value is `v2`, which refers to Sun Java System Application Server version 2 or Sun Java System Application Server version 9.1 or 9.1.1. Beginning in Jakarta EE 6, the Jakarta EE platform specification imposed stricter requirements than Jakarta EE 5 did on which JAR files can be visible to various modules within an EAR file. In particular, application clients must not have access to EJB JAR files or other JAR files in the EAR file unless references use the standard Java SE mechanisms (extensions, for example) or the Jakarta EE library-directory mechanism. Setting this property to `v2` removes these restrictions.

#### **keepSessions={false|true}**

Superseded by the `--keepstate` option.

This property can be used to specify whether active sessions of the application that is being redeployed are preserved and then restored when the redeployment is complete. Applies to HTTP sessions in a web container. Default is `false`.

##### **false**

Active sessions of the application are not preserved and restored (default).

##### **true**

Active sessions of the application are preserved and restored.

If any active session of the application fails to be preserved or restored, none of the sessions will be available when the redeployment is complete. However, the redeployment continues and a warning is logged.

To preserve active sessions, Eclipse GlassFish serializes the sessions and saves them in memory. To restore the sessions, the class loader of the newly redeployed application deserializes any sessions that were previously saved.

#### **preserveAppScopedResources**

If set to `true`, preserves any application-scoped resources and restores them during redeployment. Default is `false`.

Other available properties are determined by the implementation of the component that is being redeployed.

For components packaged as OSGi bundles (`--type=osgi`), the `deploy` subcommand accepts properties arguments to wrap a WAR file as a WAB (Web Application Bundle) at the time of deployment. The subcommand looks for a key named `UriScheme` and, if present, uses the key as a URL stream handler to decorate the input stream. Other properties are used in the decoration process. For example, the Eclipse GlassFish OSGi web container registers a URL stream handler named `webbundle`, which is used to wrap a plain WAR file as a WAB. For more information about usage, see the related example in the `deploy(1)` help page.

## Operands

### file\_archive|filepath

The operand can specify a directory or an archive file. The path to the archive that contains the application that is being redeployed. This path can be a relative path or an absolute path.

The archive can be in either of the following formats:

- An archive file, for example, `/export/JEE_apps/hello.war`. If the `--upload` option is set to `true`, this is the path to the deployable file on the local client machine.  
If the `--upload` option is set to `false`, this is the absolute path to the file on the server machine.
- A directory that contains the exploded format of the deployable archive. This is the absolute path to the directory on the server machine.  
If you specify a directory, the `--upload` option is ignored.

Whether this operand is required depends on how the application was originally deployed:

- If the application was originally deployed from a file, the archive-path operand is required. The operand must specify an archive file.
- If the application was originally deployed from a directory, the archive-path operand is optional.

## Examples

### Example 1 Redeploying a Web Application From a File

This example redeploys the web application `hello` from the `hello.war` file in the current working directory. The application was originally deployed from a file. Active sessions of the application are to be preserved and then restored when the redeployment is complete.

```
asadmin> redeploy --name hello --properties keepSessions=true hello.war
Application deployed successfully with name hello.
Command redeploy executed successfully
```

## Example 2 Redeploying a Web Application From a Directory

This example redeploys the web application `hellodir`. The application was originally deployed from a directory.

```
asadmin> redeploy --name hellodir
Application deployed successfully with name hellodir.
Command redeploy executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[deploy\(1\)](#), [get\(1\)](#), [list-components\(1\)](#), [undeploy\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# remove-library

Removes one or more library JAR files from Eclipse GlassFish

## Synopsis

```
asadmin [asadmin-options] remove-library [--help]
[--type={common|ext|app}]
library-name [library-name ... ]
```

## Description

The **remove-library** subcommand removes one or more library JAR files from Eclipse GlassFish.

The **--type** option specifies the library type and the Eclipse GlassFish directory from which the library is removed.

The library-name operand is the name of the JAR file that contains the library to be removed. To specify multiple libraries, specify multiple names separated by spaces.

The library archive file is removed from the DAS. For common and extension libraries, you must restart the DAS so the library removals are picked up by the server runtime. To remove the libraries from other server instances, synchronize the instances with the DAS by restarting them.

This command is not supported on the Windows operating system.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--type**

Specifies the library type and the Eclipse GlassFish directory from which the library is removed.

Valid values are as follows:

**common**

Removes the library files from the Common class loader directory, domain-dir/**lib**. This is the default.

**ext**

Removes the library files from the Java optional package directory, domain-dir `/lib/ext`.

**app**

Removes the library files from the application-specific class loader directory, domain-dir `/lib/applibs`.

For more information about these directories, see "[Class Loaders](#)" in Eclipse GlassFish Application Development Guide.

## Operands

**library-name**

The names of the JAR files that contain the libraries that are to be removed.

## Examples

### Example 1 Removing Libraries

This example removes the library in the archive file **mylib.jar** from the application-specific class loader directory on the default server instance.

```
asadmin> remove-library --type app mylib.jar
Command remove-library executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[add-library\(1\)](#), [list-libraries\(1\)](#)

"Class Loaders" in Eclipse GlassFish Application Development Guide

# restart-domain

Restarts the DAS of the specified domain

## Synopsis

```
asadmin [asadmin-options] restart-domain [--help]
[--debug ={true|false}]
[--domaindir domaindir]
[--force={true|false}] [--kill={false|true}]
[domain-name]
```

## Description

The **restart-domain** subcommand stops and then restarts the domain administration server (DAS) of the specified domain. If a domain is not specified, the default domain is assumed. If the domains directory contains two or more domains, the domain-name operand must be specified. If the DAS is not already running, the subcommand attempts to start it.

The **restart-domain** subcommand does not exit until the subcommand has verified that the domain has been stopped and restarted.

This subcommand is supported in local or remote mode. If you specify a host name, the subcommand assumes you are operating in remote mode, which means you must correctly authenticate to the remote server. In local mode, you normally do not need to authenticate to the server as long as you are running the subcommand as the same user who started the server.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --debug

Specifies whether the domain is restarted with [Java Platform Debugger Architecture \(JPDA\)](#) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugging enabled.

Possible values are as follows:

**true**

The domain is restarted with JPDA debugging enabled and the port number for JPDA debugging is displayed.

**false**

The domain is restarted with JPDA debugging disabled (default).

The default is the current setting of this option for the domain that is being restarted.

**--domaindir**

The domain root directory, which contains the directory of the domain that is to be restarted. If specified, the path must be accessible in the file system. The default location of the domain root directory is as-install/[domains](#).

**--force**

Specifies whether the domain is forcibly stopped immediately before it is restarted. Possible values are as follows:

**true**

The domain is forcibly stopped immediately (default).

**false**

The subcommand waits until all threads that are associated with the domain are exited before stopping the domain.

**--kill**

Specifies whether the domain is killed before it is restarted by using functionality of the operating system to terminate the domain process. Possible values are as follows:

**false**

The domain is not killed. The subcommand uses functionality of the Java platform to terminate the domain process (default).

**true**

The domain is killed. The subcommand uses functionality of the operating system to terminate the domain process.

# Operands

**domain-name**

The name of the domain you want to restart. Default is the name specified during installation, usually [domain1](#).

# Examples

## Example 1 Restarting a Domain

This example restarts `mydomain4` in the default domains directory.

```
asadmin> restart-domain mydomain4
Successfully restarted the domain
Command restart-domain executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-domain\(1\)](#), [list-domains\(1\)](#), [start-domain\(1\)](#), [stop-domain\(1\)](#)

Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# restart-instance

Restarts a running Eclipse GlassFish instance

## Synopsis

```
asadmin [asadmin-options] restart-instance [--help]
[--debug={false|true}] instance-name
```

## Description

The `restart-instance` subcommand restarts a running Eclipse GlassFish instance. This subcommand requires secure shell (SSH) to be configured on the machine where the domain administration server (DAS) is running and on the machine where the instance resides.



SSH is not required if the instance resides on a node of type `CONFIG` that represents the local host. A node of type `CONFIG` is not enabled for communication over SSH.

You may run this subcommand from any machine that can contact the DAS.

The subcommand can restart any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can restart an instance that was created by using the `create-local-instance(1)` subcommand.

When this subcommand restarts an instance, the DAS synchronizes the instance with changes since the last synchronization as follows:

- For the `config` directory, the DAS synchronizes the instance with all changes.
- For the `applications` directory and `docroot` directory, only a change to a top-level subdirectory causes the DAS to synchronize all files under that subdirectory.

If a file below a top level subdirectory is changed without a change to a file in the top level subdirectory, full synchronization is required. In normal operation, files below the top level subdirectories of these directories are not changed. If an application is deployed and undeployed, full synchronization is not necessary to update the instance with the change.

If different synchronization behavior is required, the instance must be stopped and restarted by using following sequence of subcommands:

1. `stop-instance(1)`
2. `start-instance(1)`

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--debug**

Specifies whether the instance is restarted with Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugging enabled.

Possible values are as follows:

**true**

The instance is restarted with JPDA debugging enabled and the port number for JPDA debugging is displayed.

**false**

The instance is restarted with JPDA debugging disabled.

The default is the current setting of this option for the instance that is being restarted.

## Operands

### instance-name

The name of the Eclipse GlassFish instance to restart. If the instance is not running, the subcommand displays a warning message and attempts to start the instance.

## Examples

### Example 1 Restarting a Eclipse GlassFish Instance

This example restarts the Eclipse GlassFish instance `pmdsa1`.

```
asadmin> restart-instance pmdsa1
Instance pmdsa1 was restarted.
```

Command `restart-instance` executed successfully.

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [restart-local-instance\(1\)](#), [setup-ssh\(1\)](#), [start-instance\(1\)](#), [start-local-instance\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#)

Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# restart-local-instance

Restarts a running Eclipse GlassFish instance on the host where the subcommand is run

## Synopsis

```
asadmin [asadmin-options] restart-local-instance [--help]
[--nodedir nodedir] [--node node]
[--debug={false|true}]
[--force={true|false}] [--kill={false|true}]
[instance-name]
```

## Description

The **restart-local-instance** subcommand restarts a Eclipse GlassFish instance on the host where the subcommand is run. This subcommand does not require secure shell (SSH) to be configured. You must run this command from the host where the instance resides.

The subcommand can restart any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can restart an instance that was created by using the [create-instance\(1\)](#) subcommand.

The **restart-local-instance** subcommand does not contact the domain administration server (DAS) to determine the node on which the instance resides. To determine the node on which the instance resides, the subcommand searches the directory that contains the node directories. If multiple node directories exist, the node must be specified as an option of the subcommand.

When this subcommand restarts an instance, the DAS synchronizes the instance with changes since the last synchronization as follows:

- For the **config** directory, the DAS synchronizes the instance with all changes.
- For the **applications** directory and **docroot** directory, only a change to a top-level subdirectory causes the DAS to synchronize all files under that subdirectory.

If a file below a top level subdirectory is changed without a change to a file in the top level subdirectory, full synchronization is required. In normal operation, files below the top level subdirectories of these directories are not changed. If an application is deployed and undeployed, full synchronization is not necessary to update the instance with the change.

If different synchronization behavior is required, the instance must be stopped and restarted by using following sequence of subcommands:

1. [stop-local-instance\(1\)](#)

---

## 2. `start-local-instance(1)`

This subcommand is supported in local mode. However, to synchronize the instance with the DAS, this subcommand must be run in remote mode.

# Options

## **asadmin-options**

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### **--help**

**-?**

Displays the help text for the subcommand.

### **--nodedir**

Specifies the directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is `as-install/nodes`.

### **--node**

Specifies the node on which the instance resides. This option may be omitted only if the directory that the `--nodedir` option specifies contains only one node directory. Otherwise, this option is required.

### **--debug**

Specifies whether the instance is restarted with [Java Platform Debugger Architecture \(JPDA\)](#) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugging enabled.

Possible values are as follows:

#### **true**

The instance is restarted with JPDA debugging enabled and the port number for JPDA debugging is displayed.

#### **false**

The instance is restarted with JPDA debugging disabled (default).

The default is the current setting of this option for the instance that is being restarted.

### **--force**

Specifies whether the instance is forcibly stopped immediately before it is restarted. Possible values are as follows:

#### **true**

The instance is forcibly stopped immediately (default).

**false**

The subcommand waits until all threads that are associated with the instance are exited before stopping the instance.

**--kill**

Specifies whether the instance is killed before it is restarted by using functionality of the operating system to terminate the instance process. Possible values are as follows:

**false**

The instance is not killed. The subcommand uses functionality of the Java platform to terminate the instance process (default).

**true**

The instance is killed. The subcommand uses functionality of the operating system to terminate the instance process.

# Operands

**instance-name**

The name of the Eclipse GlassFish instance to restart. If the instance is not running, the subcommand displays a warning message and attempts to start the instance.

# Examples

## Example 1 Restarting an Instance Locally

This example restarts the instance `ymlsa1` in the domain `domain1` on the host where the subcommand is run.

```
asadmin> restart-local-instance --node localhost-domain1 ymlsa1
Command restart-local-instance executed successfully.
```

# Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [restart-instance\(1\)](#), [start-instance\(1\)](#), [start-local-instance\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#)

Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# restore-domain

Restores files from backup

## Synopsis

```
asadmin [asadmin-options] restore-domain [--help]
[--long[={false|true}]]
[--filename backup-filename]
[--domainmdir domain-root-dir]
[--backupdir backup-directory]
[--backupconfig backup-config-name]
[--force[={false|true}]]
[domain-name]
```

## Description

This command restores files under the domain from a backup directory.

The `restore-domain` command is supported in local mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--long**

**-l**

Displays detailed information about the restore operation.

The default value is `false`.

**--filename**

Specifies the name of the backup file to use as the source.

**--domainmdir**

Specifies the domain root directory, the parent directory of the domain to restore. The default value is `as-install/domains`.

**--backupdir**

Specifies the directory under which the backup file is stored.

The default value is `as-install/domains/domain-dir/backups`. If the domain is not in the default location, the location is `domain-dir/backups`.

**--backupconfig**

(Supported only in Eclipse GlassFish.) The name of the domain backup configuration in the backup directory under which the backup file is stored.

**--force**

Causes the restore operation to continue even when the name of the domain to restore does not match the name of the domain stored in the backup file.

The default value is `false`.

## Operands

**domain-name**

Specifies the name of the domain to restore.

This operand is optional if only one domain exists in the Eclipse GlassFish installation.

If the specified domain name does not match the domain name stored in the backup file, an error occurs unless the `--force` option is specified.

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[backup-domain\(1\)](#), [list-backups\(1\)](#)

# rollback-transaction

Rolls back the named transaction

## Synopsis

```
asadmin [asadmin-options] rollback-transaction [--help]
[--target target]
transaction_id
```

## Description

The **rollback-transaction** subcommand rolls back the named transaction.

Before you can roll back a transaction, you must do the following:

1. Enable monitoring using the **set** subcommand. For example:

```
asadmin> set clstr1-config.monitoring-service.module-monitoring-levels.transaction-
service=HIGH
```

2. Use the **freeze-transaction-service** subcommand to halt in-process transactions.
3. Look up the active transactions using the **get** subcommand with the **--monitor** option. For example:

```
asadmin> get --monitor inst1.server.transaction-service.activeids-current
```

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This option specifies the target on which you are rolling back the transactions. Valid values are **server** or any other clustered or stand-alone instance.

# Operands

## **transaction\_id**

Identifier for the transaction to be rolled back.

## Examples

### Example 1 Using rollback-transaction command

```
% asadmin rollback-transaction 0000000000000001_00
Command rollback-transaction executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[freeze-transaction-service\(1\)](#), [recover-transactions\(1\)](#), [unfreeze-transaction-service\(1\)](#),

"[Administering Transactions](#)" in Eclipse GlassFish Administration Guide

"[Transactions](#)" in The Jakarta EE Tutorial

# rotate-log

Rotates the log file

## Synopsis

```
asadmin [asadmin-options] rotate-log [--help]
```

## Description

The **rotate-log** subcommand rotates the server log by renaming the file with a timestamp name in the format `server.log\_`date-and-time, and creating a new log file. Changes take effect dynamically, that is, server restart is not required.

The size of the log queue is configurable through the **logging.properties** file. Log rotation is based on file size or elapsed time since the last log rotation. In some circumstances, the queue might fill up, especially if the log level is set to **FINEST** and there is heavy activity on the server. In this case, the **rotate-log** subcommand can be used to rotate the server log immediately. This subcommand is also useful in creating scripts for rotating the log at convenient times.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

The server, cluster, or server instance for which logs will be rotated. If this option is omitted, logs are rotated for the default server.

## Operands

### target

Valid values are:

- **server\_name** - Default target is **server**. If no target is specified then logs are rotated for the server.

- cluster\_name - The name of a target cluster.
- instance\_name - The name of a target server instance.

## Examples

### Example 1 Rotating the Server Log

This example rotates the server log.

```
asadmin> rotate-log
Command rotate-log executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[collect-log-files\(1\)](#), [list-log-attributes\(1\)](#), [list-log-levels\(1\)](#), [set-log-attributes\(1\)](#), [set-log-levels\(1\)](#)

["Administering the Logging Service"](#) in Eclipse GlassFish Administration Guide

# set

Sets the values of configurable attributes

## Synopsis

```
asadmin [asadmin-options] set [--help]
attribute-name=value
```

## Description

The `set` subcommand uses dotted names to modify the values of one or more configurable attributes.

Attributes from the monitoring hierarchy are read-only, but configuration attributes can be modified. You can use the [list\(1\)](#) subcommand to display the dotted names that represent individual server components and subsystems. For example, a dotted name might be `server.applications.web-module`. After you discover the particular component or subsystem, you can then use the `get` subcommand to access the attributes. For more detailed information on dotted names, see the [dotted-names\(5ASC\)](#) help page.



Characters that have special meaning to the shell or command interpreter, such as \* (asterisk), should be quoted or escaped as appropriate to the shell, for example, by enclosing the argument in quotes. In multimode, quotes are needed only for arguments that include spaces, quotes, or backslash.

By modifying attributes, you can enable and disable services, and customize how an existing element functions. An `asadmin` subcommand is provided to update some elements. For example, [update-password-alias](#). However, to update other elements, you must use the `set` command. For example, you create a JDBC connection pool by using the [create-jdbc-connection-pool](#) subcommand. To change attribute settings later, you use the `set` command.

Any change made by using the `asadmin` utility subcommands or the Administration Console are automatically applied to the associated Eclipse GlassFish configuration file.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

# Operands

## attribute-name=value

Identifies the full dotted name of the attribute name and its value.

## Examples

### Example 1 Setting a JDBC Connection Pool Attribute

This example changes the steady pool size of the `DerbyPool` connection pool to 9.

```
asadmin> set resources.jdbc-connection-pool.DerbyPool.steady-pool-size=9
Command set executed successfully.
```

### Example 2 Enabling the Monitoring Service for a Monitorable Object

This example enables monitoring for the JVM.

```
asadmin> set server.monitoring-service.module-monitoring-levels.jvm=HIGH
Command set executed successfully.
```

### Example 3 Turning on Automatic Recovery for the Transaction Service

This example turns on automatic recovery for the transaction service.

```
asadmin> set server.transaction-service.automatic-recovery=true
Command set executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[get\(1\), list\(1\)](#)

[dotted-names\(5ASC\)](#)

[Eclipse GlassFish Administration Guide](#)

# set-batch-runtime-configuration

Configures the batch runtime

## Synopsis

```
asadmin [asadmin-options] set-batch-runtime-configuration [--help]
[--target target]
[--datasourcelookupname datasource-lookup-name]
[--executorservicelookupname executor-service-lookup-name]
```

## Description

The `set-batch-runtime-configuration` subcommand configures the batch runtime. The runtime uses a data source and a managed executor service to execute batch jobs. Batch runtime configuration data is stored in the `config` element in `domain.xml`.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

Specifies the target for which to configure the batch runtime. Valid values are as follows:

##### server

Configures the batch runtime for the default server instance `server` and is the default value.

##### cluster-name

Configures the batch runtime for every server instance in the cluster.

##### instance-name

Configures the batch runtime for a particular server instance.

#### --datasourcelookupname

-d

The JNDI lookup name of the data source to be used to store job information. The default data source is `jdbc/_TimerPool`.

Do not change the data source after the first batch job has been submitted to the batch runtime for execution. If the data source must be changed, stop and restart the domain and then make the change before any jobs are started or restarted. However, once the data source has been changed, information stored in the previous data source becomes inaccessible.

#### --executorservicelookupname

-x

The JNDI lookup name of the managed executor service to be used to provide threads to jobs. The default managed executor service is `concurrent/_defaultManagedExecutorService`.

The managed executor service can be changed after a batch job has been submitted to the batch runtime without impacting execution of the job.

## Examples

### Example 1 Configuring the Batch Runtime

The following example configures the batch runtime for the default server instance to use an existing managed executor service named `concurrent/myExecutor`.

```
asadmin> set-batch-runtime-configuration --executorservicelookupname
concurrent/myExecutor
Command set-batch-runtime-configuration executed successfully.
```

## Exit Status

0

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-batch-jobs\(1\)](#), [list-batch-job-executions\(1\)](#), [list-batch-job-steps\(1\)](#), [list-batch-runtime-configuration\(1\)](#)

# set-log-attributes

Sets the logging attributes for one or more loggers

## Synopsis

```
asadmin [asadmin-options] set-log-attributes [--help]
[--target=target]
attribute-name=attribute-value[:attribute-name=attribute-value]*
```

## Description

The **set-log-attributes** subcommand sets logging attributes for one or more loggers. The attributes you can set correspond to the attributes that are available in the **logging.properties** file for the domain. Depending on the attributes you set, a server restart may be necessary.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

The server domain, instance, or cluster for which logger attributes will be set. If this option is omitted, attributes are set for the default server.

## Operands

### target

Valid values are:

- `server_name` - Default target is `server`. If no target is specified then log attributes are set for the server.
- `cluster_name` - The name of a target cluster.
- `instance_name` - The name of a target server instance.

## attribute-name

The fully scoped name of the logging attribute. The `list-log-attributes` subcommand can be used to list the names of all currently defined attributes.

## attribute-value

The value to apply to the specified attribute.

The attribute values that can be specified include the following. Refer to "[Administering the Logging Service](#)" in Eclipse GlassFish Administration Guide for complete explanations of each of these values.

`com.sun.enterprise.server.logging.GFFileHandler.alarms`

Default is `false`.

`com.sun.enterprise.server.logging.GFFileHandler.excludeFields`

Default is an empty string.

`com.sun.enterprise.server.logging.GFFileHandler.file`

Default is `${com.sun.aas.instanceRoot}/logs/server.log`.

`com.sun.enterprise.server.logging.GFFileHandler.flushFrequency`

Default is `1`.

`com.sun.enterprise.server.logging.GFFileHandler.formatter`

Default is `com.sun.enterprise.server.logging.UniformLogFormatter`.

`com.sun.enterprise.server.logging.GFFileHandler.logtoConsole`

Default is `false`.

`com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles`

Default is `0`.

`com.sun.enterprise.server.logging.GFFileHandler.multiLineMode`

Default is `true`.

`com.sun.enterprise.server.logging.GFFileHandler.retainErrorsStaticsForHours`

Default is `0`.

`com.sun.enterprise.server.logging.GFFileHandler.rotationLimitInBytes`

Default is `2000000`.

`com.sun.enterprise.server.logging.GFFileHandler.rotationTimeLimitInMinutes`

Default is `0`.

`com.sun.enterprise.server.logging.SyslogHandler.useSystemLogging`

Default is `false`.

**handlers**

Default is `java.util.logging.ConsoleHandler`.

**java.util.logging.ConsoleHandler.formatter**

Default is `com.sun.enterprise.server.logging.UniformLogFormatter`.

**java.util.logging.FileHandler.count**

Default is 1.

**java.util.logging.FileHandler.formatter**

Default is `java.util.logging.XMLFormatter`.

**java.util.logging.FileHandler.limit**

Default is 5000.

**java.util.logging.FileHandler.pattern**

Default is %h/java%u.log.

**log4j.logger.org.hibernate.validator.util.Version**

Default is warn.

## Examples

### Example 1 Setting the Maximum Number of Log History Files to Maintain

This example sets to 8 the maximum number of log history files for the server as a whole.

```
asadmin> set-log-attributes --target=server \
com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles=8
com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles logging
attribute set with value 8.
These logging attributes are set for server.
Command set-log-attributes executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

---

## See Also

[asadmin\(1M\)](#)

[collect-log-files\(1\)](#), [list-log-attributes\(1\)](#), [list-log-levels\(1\)](#), [rotate-log\(1\)](#), [set-log-levels\(1\)](#)

"[Administering the Logging Service](#)" in Eclipse GlassFish Administration Guide

# set-log-file-format

Sets the formatter to be used for the server log file

## Synopsis

```
asadmin [asadmin-options] set-log-file-format [--help]
[--target target]
[formatter]
```

## Description

The **set-log-file-format** subcommand sets the formatter to be used for the server log file for the specified target.

Eclipse GlassFish provides the ULF (UniformLogFormatter) and ODL (Oracle Diagnostics Logging) formatters. A custom formatter can also be used by specifying the fully qualified name of a class that extends the `java.util.logging.Formatter` class.

The custom formatter class can be packaged in a JAR file and placed in `domain/lib/ext`, or implemented as an HK2 service and the JAR containing the formatter implementation installed in `glassfish/modules`.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --target

Specifies the target for which the formatter is being set. Specify the name of the server domain, instance, or cluster. If this option is omitted, logger attributes are set for the default server.

## Operands

### formatter

Specifies the fomatter to be used for the server log file. Valid values are ULF, ODL, or the fully

qualified name of the custom formatter class to be used to render the log files. The default value is ODL.

## Examples

### Example 1 Setting the Log File Format

This example sets the server log file format to `ULF` for `server1`.

```
asadmin> set-log-file-format --target server1 ULF
Command set-log-file-format executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-loggers\(1\)](#)

"[Administering the Logging Service](#)" in Eclipse GlassFish Administration Guide

# set-log-levels

Sets the log level for one or more loggers

## Synopsis

```
asadmin [asadmin-options] set-log-levels [--help]
[--target=target]
logger-name=logger-level[:logger-name=logger-level]*
```

## Description

The **set-log-levels** subcommand sets the log level for one or more loggers. Changes take effect dynamically. Depending on the log levels you set, a server restart may be necessary.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --target

The server instance or cluster for which log levels will be set. Valid values are:

- **server** - The default server instance. If no target is specified then log levels are set for the default server instance.
- **cluster-name** - The name of a cluster.
- **instance-name** - The name of a standalone server instance.

## Operands

### logger-name

The name of the logger. The **list-log-levels** subcommand can be used to list the names of the current loggers.

## logger-level

The level to set for the logger. Log level values are **SEVERE**, **WARNING**, **INFO**, **CONFIG**, **FINE**, **FINER**, and **FINEST**. The default setting is **INFO**.

# Examples

## Example 1 Setting a Log Level for a Logger

This example sets the log level of the web container logger to **WARNING**.

```
asadmin> set-log-levels jakarta.enterprise.system.container.web=WARNING
Command set-log-level executed successfully.
```

## Example 2 Setting the Log Level for Multiple Loggers

This example sets the log level of the web container logger to **FINE** and the log level of the EJB container logger to **SEVERE**:

```
asadmin set-log-levels jakarta.enterprise.system.container.web=FINE:
jakarta.enterprise.system.container.ejb=SEVERE
Command set-log-level executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[collect-log-files\(1\)](#), [list-log-attributes\(1\)](#), [list-log-levels\(1\)](#), [rotate-log\(1\)](#), [set-log-attributes\(1\)](#)

["Administering the Logging Service"](#) in Eclipse GlassFish Administration Guide



# setup-local-dcom

Sets up DCOM on a host

## Synopsis

```
asadmin [asadmin-options] setup-local-dcom [--help]
[--verbose={false|true}]
--force={false|true}
```

## Description

The **setup-local-dcom** subcommand sets up the Distributed Component Object Model (DCOM) remote protocol on the host where the subcommand is run. The DCOM remote protocol is available only on Windows systems.

This subcommand must be run by the operating-system-level administrator user on the host where DCOM is being set up. Before running this command, ensure that items in the Windows operating system are set as described in " [Windows Operating System Settings](#)" in Eclipse GlassFish High Availability Administration Guide.

Setting up DCOM on a host ensures that scripts can be run on the host from a remote host. To run scripts on the host from a remote host, the Windows user must be allowed full control over some Windows registry keys.

In some versions of Windows, only the user **NT SERVICE\TrustedInstaller** has full control over these Windows registry keys. If the version of Windows on a host is configured in this way, this subcommand modifies these keys to allow full control over them for the Windows user.



This subcommand might modify the permissions of some keys in the Windows registry. Before running this command, back up the Windows registry.

By default, the subcommand prompts you to confirm that you want to update the Windows registry. To run the subcommand without being prompted, set the **--force** option to **true**.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--verbose**

**-v**

Specifies whether the subcommand displays information about the operations that are performed to set up DCOM on the host.

Possible values are as follows:

**false**

No information about the operations that are performed to set up DCOM is displayed (default).

**true**

The subcommand displays information about the operations that are performed to set up DCOM on the host.

**--force**

**-f**

Specifies whether the subcommand prompts you to confirm that you want to update the Windows registry.

Possible values are as follows:

**false**

You are prompted to confirm that you want to update the Windows registry (default).

**true**

The subcommand forcibly updates the Windows registry without prompting you.

## Examples

### Example 1 Setting Up DCOM on a Host

This example sets up DCOM on the host where the subcommand is run.

```
asadmin> setup-local-dcom
```

Caution: This command might modify the permissions of some keys in the Windows registry.

Before running this command, back up the Windows registry.

The modification allows the Windows user full control over these keys.

Are you sure that you want to edit the Windows registry? If so, type yes in full: yes

Command setup-local-dcom executed successfully.

## Example 2 Forcibly Setting Up DCOM on a Host

This example sets up DCOM without prompting for confirmation that the user wants to update the Windows registry.

```
asadmin> setup-local-dcom --force=true
Command setup-local-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

"[Windows Operating System Settings](#)" in Eclipse GlassFish High Availability Administration Guide

# setup-ssh

Sets up an SSH key on specified hosts

## Synopsis

```
asadmin [asadmin-options] setup-ssh [--help]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile] [--sshppublickeyfile ssh-public-keyfile]
[--generatekey={false|true}]
host-list
```

## Description

The **setup-ssh** subcommand sets up a secure shell (SSH) key on the hosts that are specified as the operand of the subcommand. This key enables Eclipse GlassFish to use public-key authentication for authentication of the user's SSH login on remote hosts.

SSH ensures that Eclipse GlassFish clusters that span multiple hosts can be administered centrally. When a user runs a subcommand for cluster administration that acts on multiple hosts, the subcommand is propagated from the domain administration server (DAS) host to remote hosts. To propagate subcommands that act on a Eclipse GlassFish instance that is not running, or on a node where no instances are running, Eclipse GlassFish uses SSH. SSH provides confidentiality and security for data that is exchanged between the DAS and remote hosts.

Public-key authentication uses an SSH key pair that comprises the following keys:

- A private key, which is stored in a secure location on the DAS host and which may be protected with a passphrase
- The public key, which is stored on all the remote hosts with which the DAS communicates

The subcommand does not require any configuration information from the DAS and does not modify the configuration of the DAS.

This subcommand is supported in local mode only.

### Prerequisites for Using the **setup-ssh** Subcommand

To use the **setup-ssh** subcommand, the SSH user must be able to use SSH to log in to remote hosts where SSH is to be set up. Specifically, the following prerequisites must be met:

- The [ssh\(1\)](#) client is installed on the DAS host and is accessible through the DAS user's path.
- The [sshd\(1M\)](#) daemon is installed and running on all hosts where an SSH key is to be set up.

- The user that the `--sshuser` option specifies has an SSH login on all hosts where an SSH key is to be set up.
- The `ssh-keygen(1)` utility is installed on the DAS host either at the default location or in a location that is defined in the DAS user's path.
- On Windows systems, the SSH package for [Cygwin](http://www.cygwin.com/) (<http://www.cygwin.com/>) or an [MKS Software](http://www.mkssoftware.com/) (<http://www.mkssoftware.com/>) toolkit that provides SSH is installed.

### Behavior of the `setup-ssh` Subcommand

The subcommand sets up SSH connectivity between the DAS host and remote hosts by automating the following tasks:

- Generating an SSH key pair. If no SSH key pair exists, the default behavior of the subcommand is to prompt the user to generate an SSH key pair. The SSH key pair is generated without an encryption passphrase. If a passphrase-protected key pair is required, the key pair must be generated manually by using the SSH command `ssh-keygen(1)`.
- Distributing the public key. The subcommand appends the content of the public key file to the user-home/.ssh/authorized\_keys file on each remote host. By default, the subcommand locates the public key file in the user-home/.ssh directory on the host where the subcommand is run. If the user-home/.ssh/authorized\_keys file does not exist on a host, the subcommand creates the file. user-home is the user's home directory on a host.

To distribute the public key, authentication of the user's SSH login is required. If the private key is protected by a passphrase, the passphrase is also required. By default, the subcommand prompts the user for the password and, if necessary, the passphrase. To distribute the public key without being prompted, run the subcommand as follows:

- Set the `--interactive` option of the `asadmin(1M)` utility to `false`.
  - Set the `--passwordfile` option of the `asadmin` utility to a file in which the `AS_ADMIN_SSHPASSWORD` entry specifies the SSH user's password for logging in to the specified hosts.
  - If a passphrase is required, ensure that the file that `--passwordfile` option of the `asadmin` utility specifies also contains an entry for `AS_ADMIN_SSHKEYPASSPHRASE`.
- If public key authentication is already set up on a host, the subcommand informs the user that public key authentication is already set up and does not distribute the key to the host.

# Options

## `asadmin-options`

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--sshport**

The port to use for SSH connections to the host where SSH is being set up. The default is 22.

**--sshuser**

The SSH user on the remote host that is to run the process for setting up SSH on that host. The default is the user that is running this subcommand. To ensure that the DAS can read this user's SSH private key file, specify the user that is running the DAS process.

**--sshkeyfile**

The absolute path to the SSH private key file for user that the **--sshuser** option specifies. This file is used for authentication to the **sshd** daemon on the host.

The user that is running this subcommand must be able to reach the path to the key file and read the key file.

The default is a key file in the user's **.ssh** directory on the host where the subcommand is run. If multiple key files are found, the subcommand uses the following order of preference:

1. **id\_rsa**
2. **id\_dsa**
3. **identity**

**--sshpublickeyfile**

The absolute path to the SSH public key file for user that the **--sshuser** option specifies. The content of the public key file is appended to the user's **.ssh/authorized\_keys** file on each host where SSH is being set up. If the **.ssh/authorized\_keys** file does not exist on a host, the subcommand creates the file.

The user that is running this subcommand must be able to reach the path to the key file and read the key file.

The default is a key file in the user's **.ssh** directory on the host where the subcommand is run. If multiple key files are found, the subcommand uses the following order of preference:

1. **id\_rsa.pub**
2. **id\_dsa.pub**
3. **identity.pub**

**--generatekey**

Specifies whether the subcommand generates the SSH key files without prompting the user. Possible values are as follows:

**true**

The subcommand generates the SSH key files without prompting the user.

**false**

The behavior of the subcommand depends on whether the SSH key files exist:

- If the SSH key files exist, the subcommand does not generate the files.
- If the SSH key files do not exist, the behavior of the subcommand depends on the value of the `--interactive` option of the `asadmin` utility:
  - If the `--interactive` option is `true`, the subcommand prompts the user to create the files.
  - If the `--interactive` option is `false`, the subcommand fails. This value is the default.

## Operands

### host-list

A space-separated list of the names of the hosts where an SSH key is to be set up.

## Examples

### Example 1 Setting Up an SSH Key

This example sets up an SSH key for the user `gfuser` on the hosts `sj03` and `sj04`. The key file is not generated but is copied from the user's `.ssh` directory on the host where the subcommand is running.

```
asadmin> setup-ssh sj03 sj04
Enter SSH password for gfuser@sj03>
Copied keyfile /home/gfuser/.ssh/id_rsa.pub to gfuser@sj03
Successfully connected to gfuser@sj03 using keyfile /home/gfuser/.ssh/id_rsa
Copied keyfile /home/gfuser/.ssh/id_rsa.pub to gfuser@sj04
Successfully connected to gfuser@sj04 using keyfile /home/gfuser/.ssh/id_rsa
Command setup-ssh executed successfully.
```

### Example 2 Generating and Setting Up an SSH Key

This example generates and sets up an SSH key for the user `gfuser` on the hosts `sua01` and `sua02`.

```
asadmin> setup-ssh --generatekey=true sua01 sua02
Enter SSH password for gfuser@sua01>
Created directory /home/gfuser/.ssh
/usr/bin/ssh-keygen successfully generated the identification /home/gfuser/.ssh/id_rsa
Copied keyfile /home/gfuser/.ssh/id_rsa.pub to gfuser@sua01
Successfully connected to gfuser@sua01 using keyfile /home/gfuser/.ssh/id_rsa
Copied keyfile /home/gfuser/.ssh/id_rsa.pub to gfuser@sua02
Successfully connected to gfuser@sua02 using keyfile /home/gfuser/.ssh/id_rsa
Command setup-ssh executed successfully.
```

## Exit Status

0

command executed successfully

1

error in executing the command

## See Also

[asadmin\(1M\)](#)

[ssh\(1\)](#), [ssh-keygen\(1\)](#)

[sshd\(1M\)](#)

Cygwin Information and Installation (<http://www.cygwin.com/>), MKS Software (<http://www.mkssoftware.com/>)

# set-web-context-param

Sets a servlet context-initialization parameter of a deployed web application or module

## Synopsis

```
asadmin [asadmin-options] set-web-context-param [--help]
--name=context-param-name
{--value=value|--ignoredescriptoritem={false|true}}
[--description=description] application-name[/module]
```

## Description

The `set-web-context-param` subcommand sets a servlet context-initialization parameter of one of the following items:

- A deployed web application
- A web module in a deployed Java Platform, Enterprise Edition (Jakarta EE) application

The application must already be deployed. Otherwise, an error occurs.

This subcommand enables you to change the configuration of a deployed application without the need to modify the application's deployment descriptors and repackage and redeploy the application.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--name**

The name of the servlet context-initialization parameter that is to be set.

**--value**

The value to which the servlet context-initialization parameter is to be set. Either the `--value` option or the `--ignoredescriptoritem` option must be set.

**--ignoreddescriptoritem**

Specifies whether the servlet context-initialization parameter is ignored if it is set in the application's deployment descriptor. When a parameter is ignored, the application behaves as if the parameter had never been set in the application's deployment descriptor. The behavior of an application in this situation depends on the application.

The possible values are as follows:

**false**

The value is not ignored (default).

**true**

The value is ignored.

Either the **--value** option or the **--ignoreddescriptoritem** option must be set.



Do not use the **--ignoreddescriptoritem** option to unset a servlet context-initialization parameter that has previously been set by using the **set-web-context-param** subcommand. Instead, use the **unset-web-context-param(1)** subcommand for this purpose.

**--description**

An optional textual description of the context parameter that is being set.

# Operands

**application-name**

The name of the application. This name can be obtained from the Administration Console or by using the **list-applications(1)** subcommand.

The application must already be deployed. Otherwise, an error occurs.

**module**

The relative path to the module within the application's enterprise archive (EAR) file. The path to the module is specified in the **module** element of the application's **application.xml** file.

module is required only if the servlet context-initialization parameter applies to a web module of a Jakarta EE application. If specified, module must follow application-name, separated by a slash (/). For example, the **application.xml** file for the **myApp** application might specify the following web module:

```
<module>
  <web>
    <web-uri>myWebModule.war</web-uri>
  </web>
</module>
```

The module would be specified as the operand of this command as `myApp/myWebModule.war`.

## Examples

### Example 1 Setting a Servlet Context-Initialization Parameter for a Web Application

This example sets the servlet context-initialization parameter `javax.faces.STATE_SAVING_METHOD` of the web application `basic-ezcomp` to `client`. The description `The location where the application's state is preserved` is provided for this parameter.

```
asadmin> set-web-context-param --name=javax.faces.STATE_SAVING_METHOD  
--description="The location where the application's state is preserved"  
--value=client basic-ezcomp
```

Command `set-web-context-param` executed successfully.

### Example 2 Ignoring a Servlet Context-Initialization Parameter That Is Defined in a Deployment Descriptor

This example ignores the servlet context-initialization parameter `javax.faces.PROJECT_STAGE` of the web application `basic-ezcomp`.

```
asadmin> set-web-context-param --name=javax.faces.PROJECT_STAGE  
--ignoredescriptoritem=true  
basic-ezcomp
```

Command `set-web-context-param` executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-web-context-param\(1\)](#), [unset-web-context-param\(1\)](#)

# set-web-env-entry

Sets an environment entry for a deployed web application or module

## Synopsis

```
asadmin [asadmin-options] set-web-env-entry [--help]
--name=env-entry-name --type=env-entry-type
{--value=value|--ignoredescriptoritem={true|false}}
[--description=description] application-name[/module]
```

## Description

The **set-web-env-entry** subcommand sets an environment entry for one of the following items:

- A deployed web application
- A web module in a deployed Java Platform, Enterprise Edition (Jakarta EE) application

The application must already be deployed. Otherwise, an error occurs.

An application uses the values of environment entries to customize its behavior or presentation.

This subcommand enables you to change the configuration of a deployed application without the need to modify the application's deployment descriptors and repackage and redeploy the application.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--name**

The name of the environment entry that is to be set. The name is a JNDI name relative to the **java:comp/env** context. The name must be unique within a deployment component.

**--type**

The fully-qualified Java type of the environment entry value that is expected by the application's

code. This type must be one of the following Java types:

- `java.lang.Boolean`
- `java.lang.Byte`
- `java.lang.Character`
- `java.lang.Double`
- `java.lang.Float`
- `java.lang.Integer`
- `java.lang.Long`
- `java.lang.Short`
- `java.lang.String`

#### --value

The value to which the environment entry is to be set. If the `--type` is `java.lang.Character`, the value must be a single character. Otherwise, the value must be a string that is valid for the constructor of the specified type.

Either the `--value` option or the `--ignoreddescriptoritem` option must be set.

#### --ignoreddescriptoritem

Specifies whether the environment entry is ignored if it is set in the application's deployment descriptor. When an environment entry is ignored, the application behaves as if the entry had never been set in the application's deployment descriptor. The behavior of an application in this situation depends on the application.

The possible values are as follows:

##### false

The value is not ignored (default).

##### true

The value is ignored.

Either the `--value` option or the `--ignoreddescriptoritem` option must be set.



Do not use the `--ignoreddescriptoritem` option to unset an environment entry that has previously been set by using the `set-web-env-entry` subcommand. Instead, use the `unset-web-env-entry(1)` subcommand for this purpose.

#### --description

An optional textual description of the environment entry that is being set.

# Operands

## application-name

The name of the application. This name can be obtained from the Administration Console or by using the `list-applications(1)` subcommand.

The application must already be deployed. Otherwise, an error occurs.

## module

The relative path to the module within the application's enterprise archive (EAR) file. The path to the module is specified in the `module` element of the application's `application.xml` file.

`module` is required only if the environment entry applies to a web module of a Jakarta EE application. If specified, `module` must follow `application-name`, separated by a slash (`/`).

For example, the `application.xml` file for the `myApp` application might specify the following web module:

```
<module>
  <web>
    <web-uri>myWebModule.war</web-uri>
  </web>
</module>
```

The module would be specified as the operand of this command as `myApp/myWebModule.war`.

# Examples

## Example 1 Setting an Environment Entry for a Web Application

This example sets the environment entry `Hello User` of the application `hello` to `techscribe`. The Java type of this entry is `java.lang.String`.

```
asadmin> set-web-env-entry --name="Hello User"
--type=java.lang.String --value=techscribe
--description="User authentication for Hello application" hello
```

Command `set-web-env-entry` executed successfully.

## Example 2 Ignoring an Environment Entry That Is Defined in a

Deployment Descriptor

This example ignores the environment entry `Hello Port` of the web application `hello`.

```
asadmin> set-web-env-entry --name="Hello Port"
--type=java.lang.Integer --ignoredescriptoritem=true hello
```

```
Command set-web-env-entry executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [list-web-env-entry\(1\)](#), [unset-web-env-entry\(1\)](#)

# show-component-status

Displays the status of the deployed component

## Synopsis

```
asadmin [asadmin-options] show-component-status [--help]
[--target target] component-name
```

## Description

The **show-component-status** subcommand gets the status (either enabled or disabled) of the deployed component.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --target

This option specifies the target on which you are showing the component status. Valid values are:

##### server

Shows the component status for the default server instance **server** and is the default value.

##### domain

Shows the component status for the domain.

##### cluster\_name

Shows the component status for the cluster.

##### instance\_name

Shows the component status for a clustered or stand-alone server instance.

# Operands

## component-name

The name of the component whose status is to be listed.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. To list multiple versions, you can use an asterisk (\*) as a wildcard character. For more information about module and application versions, see "[Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

## Examples

### Example 1 Showing the Status of a Component

This example gets the status of the MEjbApp component.

```
asadmin> show-component-status MEjbApp
Status of MEjbApp is enabled
Command show-component-status executed successfully.
```

## Exit Status

0

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [list-sub-components\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# start-cluster

Starts a cluster

## Synopsis

```
asadmin [asadmin-options] start-cluster [--help]
[--autohadboverride={true|false}]
[--verbose={false|true}] cluster-name
```

## Description

The **start-cluster** subcommand starts a cluster by starting all Eclipse GlassFish instances in the cluster that are not already running. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured on the host where the domain administration server (DAS) is running and on all hosts where instances in the cluster reside.



If all instances reside on the same host as the DAS, DCOM or SSH is not required. You might require to start a cluster in which instances reside on hosts where DCOM or SSH is not configured that are remote from the DAS. In this situation, run the **start-local-instance(1)** subcommand for each instance from the host where the instance resides.

You may run this subcommand from any host that can contact the DAS.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the **asadmin(1M)** help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --autohadboverride

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

**--verbose**

Specifies whether additional status information is displayed when the cluster is started. Valid values are as follows:

**true**

Displays the command to start each instance in the cluster and whether the attempt to start each instance succeeded.

**false**

Displays no additional status information (default).

## Operands

**cluster-name**

The name of the cluster to start.

## Examples

### Example 1 Starting a Cluster

This example starts the cluster `ymlcluster`. Additional status information is displayed when the cluster is started.

```
asadmin> start-cluster --verbose ymlcluster
start-instance yml-i-sr1-usca-02
start-instance yml-i-sr1-usca-01
```

```
The command start-instance executed successfully for:
yml-i-sr1-usca-02 yml-i-sr1-usca-01
```

```
Command start-cluster executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[create-cluster\(1\)](#), [delete-cluster\(1\)](#), [list-clusters\(1\)](#), [setup-ssh\(1\)](#), [start-local-instance\(1\)](#), [stop-cluster\(1\)](#), [validate-dcom\(1\)](#)

# start-database

Starts the Java DB

## Synopsis

```
asadmin [asadmin-options] start-database [--help]
[--jvmoptions jvm-options]
[--dbhost host] [--dbport port-no]
[--dbhome db-file-path]
```

## Description

The `start-database` subcommand starts the Java DB server that is available for use with Eclipse GlassFish. Java DB is based upon Apache Derby. Use this subcommand only for working with applications deployed to the server.

When you start Java DB server by using the `start-database` subcommand, the database server is started in Network Server mode. Clients connecting to it must use the Java DB ClientDriver. For details on connecting to the database, refer to the Apache Derby documentation.

When the database server starts, or a client connects to it successfully, the following files are created:

- The `derby.log` file that contains the database server process log along with its standard output and standard error information
- The database files that contain your schema (for example, database tables)

These files are created at the location that is specified by the `--dbhome` option. To create the database files at a particular location, you must set the `--dbhome` option. If the `--dbhome` option is not specified, the `start-database` subcommand determines where to create these files as follows:

- If the current working directory contains a file that is named `derby.log`, the `start-database` subcommand creates the files in the current working directory.
- Otherwise, the `start-database` subcommand creates the files in the `as-install/databases` directory.

The `start-database` subcommand starts the database process, even if it cannot write to the log file.

This subcommand is supported in local mode only.

## Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

-?

Displays the help text for the subcommand.

### --jvmoptions

A space-separated list of command-line options that are passed to the Java application launcher when the database is started. By default, no options are passed.

The format of an option depends on whether the option has a name and a value or only a name:

- If the option has a name and a value, the format is option-name=value.
- If the option has only a name, the format is option-name. For example, `-Xmx512m`.

### --dbhost

The host name or IP address of the Java DB server process. The default is the IP address 0.0.0.0, which denotes all network interfaces on the host where you run the `start-database` subcommand.

### --dbport

The port number where the Java DB server listens for client connections. This port must be available for the listen socket, otherwise the database server will not start. The default is 1527.

### --dbhome

The absolute path to the directory where the database files and the `derby.log` file are created. If the `--dbhome` option is not specified, the `start-database` subcommand determines where to create these files as follows:

- If the current working directory contains a file that is named `derby.log`, the `start-database` subcommand creates the files in the current working directory.
- Otherwise, the `start-database` subcommand creates the files in the `as-install/databases` directory.

To create the database files at a particular location, you must set the `--dbhome` option.

## Examples

### Example 1 Starting Java DB

This example starts Java DB on the host `host1` and port 5001.

```
asadmin> start-database --dbhost host1 --dbport 5001 --terse=true
Starting database in the background. Log redirected to
/opt/SUNWappserver/databases/derby.log.
```

## Example 2 Starting Java DB With Options for the Java Application

### Launcher

This example starts Java DB with the options for setting the minimum heap memory size to 128 megabytes and the maximum heap memory size to 512 megabytes.

```
asadmin> start-database --jvmoptions="-Xms128m -Xmx512m" --terse=true
Starting database in the background.
Log redirected to /export/glassfish7/glassfish/databases/derby.log.
```

## Exit Status

The exit status applies to errors in executing the `asadmin` utility. For information on database errors, see the `derby.log` file. This file is located in the directory you specify by using the `--dbhome` option when you run the `start-database` subcommand. If you did not specify `--dbhome`, the value of `DERBY_INSTALL` defaults to `as-install/javadb`.

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[stop-database\(1\)](#)

["Administering Database Connectivity" in Eclipse GlassFish Administration Guide](#)

For more information about the Java application launcher, see the reference page for the operating system that you are using:

- Oracle Solaris and Linux: java - the Java application launcher (<http://docs.oracle.com/javase/6/docs/technotes/tools/solaris/java.html>)

- 
- Windows: java - the Java application launcher (<http://docs.oracle.com/javase/6/docs/technotes/tools/windows/java.html>)

# start-domain

Starts the DAS of the specified domain

## Synopsis

```
asadmin [asadmin-options] start-domain [--help]
[--debug={true|false}] [--suspend={true|false}] [--domaindir domain-dir]
[--dry-run={true|false}] [--upgrade={true|false}]
[--verbose={true|false}] [--watchdog={true|false}]
[domain-name]
```

## Description

The **start-domain** subcommand starts the domain administration server (DAS) of the specified domain. If a domain is not specified, the default domain is assumed. If the domains directory contains two or more domains, the domain-name operand must be specified.



On the Windows platform, processes can bind to the same port. To avoid this problem, do not start multiple domains with the same port number at the same time.

This subcommand is supported in local mode only.



In Eclipse GlassFish, the **start-domain** subcommand prompts for a new admin user password if no password has been set for the admin user. Additionally, the admin user password must not be blank if secure administration is enabled; otherwise, the **start-domain** subcommand fails.

To provide the new admin user password, you can use the **--passwordfile** utility option of the **asadmin(1M)** command after adding the entry **AS\_ADMIN\_NEWPASSWORD** to the password file.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the **asadmin(1M)** help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--debug****-d**

Specifies whether the domain is started with Java Platform Debugger Architecture (JPDA) (<https://docs.oracle.com/en/java/javase/11/docs/specs/jpda/conninv.html>) debugging enabled. With debugging enabled extra exceptions can be printed. Possible values are as follows:

**true**

The instance is started with JPDA debugging enabled and the port number for JPDA debugging is displayed.

**false**

The instance is started with JPDA debugging disabled (default).

**--suspend****-s**

Specifies whether the domain is started with Java Platform Debugger Architecture (JPDA) (<https://docs.oracle.com/en/java/javase/11/docs/specs/jpda/conninv.html>) debugging enabled and suspend the newly started VM before the main class loads. When a debugger connects, it can send a JDWP command to resume the suspended VM. With debugging enabled extra exceptions can be printed. Possible values are as follows:

**true**

The instance is started with JPDA debugging enabled and a suspendPolicy of **SUSPEND\_ALL**. The port number for JPDA debugging is displayed.

**false**

The instance is started with JPDA debugging disabled (default).

**--dry-run****-n**

Suppresses actual starting of the domain. Instead, **start-domain** displays the full java command that would be used to start the domain, including all options. Reviewing this command can be useful to confirm JVM options and when troubleshooting startup issues.

The default value is **false**.

**--domaindir**

The domain root directory, which contains the directory of the domain that is to be restarted. If specified, the path must be accessible in the file system. The default location of the domain root directory is `as-install/domains`.

**--upgrade**

Specifies whether the configuration of the domain administration server (DAS) is upgraded to the current release. Normally, if the subcommand detects that the configuration is from an older release of Eclipse GlassFish, the configuration is upgraded automatically before being started. You

should not need to use this option explicitly.

Possible values are as follows:

**true**

When the domain is started, the configuration is modified to be compatible with this release of Eclipse GlassFish, and the Eclipse GlassFish process stops.

**false**

The configuration of the DAS is not updated (default).

**--verbose****-v**

Specifies whether detailed information about the domain is displayed in the console window where the subcommand is run.

Possible values are as follows:

**true**

Detailed startup messages and log messages about the domain are displayed in the console window where the subcommand is run. If the domain is later restarted by running the [restart-domain\(1\)](#) subcommand from a different console window, messages continue to be displayed in the original console window.

You can kill the Eclipse GlassFish process by typing **CTRL-C** in the console window.

You can kill the Eclipse GlassFish process and obtain a thread dump for the server by typing one of the following key combinations in the console window:

- **CTRL-\** on UNIX systems
- **CTRL-Break** on Windows systems

**false**

Detailed information is not displayed (default).

**--watchdog****-w**

Specifies whether limited information about the domain is displayed in the console window where the subcommand is run. The **--watchdog** option is similar to **--verbose** but does not display the detailed startup messages and log messages. This option is useful when running the **asadmin** utility in the background or with no attached console.

Possible values are as follows:

**true**

Limited information is displayed in the console window.

**false**

Limited information is not displayed in the console window (default).

# Operands

## domain-name

The unique name of the domain you want to start.

This operand is optional if only one domain exists in the Eclipse GlassFish installation.

## Examples

### Example 1 Starting a Domain

This example starts `mydomain4` in the default domains directory.

```
asadmin> start-domain mydomain4
Waiting for DAS to start. .....
Started domain: mydomain4
Domain location: /myhome/glassfish7/glassfish/domains/mydomain4
Log file: /myhome/glassfish7/glassfish/domains/mydomain4/logs/server.log
Admin port for the domain: 4848
Command start-domain executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-domain\(1\)](#), [delete-domain\(1\)](#), [list-domains\(1\)](#), [restart-domain\(1\)](#), [stop-domain\(1\)](#)

Java Platform Debugger Architecture (JPDA) (<https://docs.oracle.com/en/java/javase/11/docs/specs/jpda/conninv.html>)

# start-instance

Starts a Eclipse GlassFish instance

## Synopsis

```
asadmin [asadmin-options] start-instance [--help]
[--debug={false|true}] [--sync={normal|full|none}]
instance-name
```

## Description

The **start-instance** subcommand starts a Eclipse GlassFish instance. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured on the machine where the domain administration server (DAS) is running and on the machine where the instance resides.



DCOM or SSH is not required if the instance resides on a node of type **CONFIG** that represents the local host. A node of type **CONFIG** is not enabled for remote communication over DCOM or SSH.

You may run this subcommand from any machine that can contact the DAS.

The subcommand can start any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can start an instance that was created by using the **create-local-instance(1)** subcommand.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the **asadmin(1M)** help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--debug**

Specifies whether the instance is started with **Java Platform Debugger Architecture (JPDA)** (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugging enabled.

Possible values are as follows:

**true**

The instance is started with JPDA debugging enabled and the port number for JPDA debugging is displayed.

**false**

The instance is started with JPDA debugging disabled (default).

**--sync**

The type of synchronization between the DAS and the instance's files when the instance is started. Possible values are as follows:

**none**

The DAS does not synchronize the instance's files with any changes. This type of synchronization minimizes the time that is required to start the instance.

**normal**

The DAS synchronizes the instance with changes since the last synchronization as follows:

- For the **config** directory, the DAS synchronizes the instance with all changes.
- For the **applications** directory and **docroot** directory, only a change to a top-level subdirectory causes the DAS to synchronize all files under that subdirectory.

If a file below a top level subdirectory is changed without a change to a file in the top level subdirectory, full synchronization is required. In normal operation, files below the top level subdirectories of these directories are not changed. If an application is deployed and undeployed, full synchronization is not necessary to update the instance with the change.

This value is the default.

**full**

The DAS synchronizes the instance with all of the instance's files, regardless of whether the files have changed since the last synchronization. This type of synchronization might delay the startup of the instance while the DAS updates all files in the instance's directories.

# Operands

## instance-name

The name of the Eclipse GlassFish instance to start.

# Examples

## Example 1 Starting a Eclipse GlassFish Instance

This example starts the Eclipse GlassFish instance `pmdsa1`.

```
asadmin> start-instance pmdsa1
Waiting for the server to start .....
Successfully started the instance: pmdsa1
instance Location: /export/glassfish7/glassfish/nodes/localhost/pmdsa1
Log File: /export/glassfish7/glassfish/nodes/localhost/pmdsa1/logs/server.log
Admin Port: 24848
Command start-local-instance executed successfully.
The instance, pmdsa1, was started on host localhost

Command start-instance executed successfully.
```

## Example 2 Starting a Eclipse GlassFish Instance With JPDA Debugging Enabled

Enabled

This example starts the Eclipse GlassFish instance `ymlsa1` with JPDA debugging enabled.

```
asadmin> start-instance --debug=true ymlsa1
Waiting for the server to start .....
Successfully started the instance: ymlsa1
instance Location: /export/glassfish7/glassfish/nodes/localhost/ymlsa1
Log File: /export/glassfish7/glassfish/nodes/localhost/ymlsa1/logs/server.log
Admin Port: 24849
Debugging is enabled. The debugging port is: 29010
Command start-local-instance executed successfully.
The instance, ymlsa1, was started on host localhost

Command start-instance executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [setup-ssh\(1\)](#),  
[start-domain\(1\)](#), [start-local-instance\(1\)](#), [stop-domain\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#),  
[validate-dcom\(1\)](#)

Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# start-local-instance

Starts a Eclipse GlassFish instance on the host where the subcommand is run

## Synopsis

```
asadmin [asadmin-options] start-local-instance [--help]
[--nodedir node-dir] [--node node]
[--debug={false|true}] [--dry-run={true|false}]
[--sync={normal|full|none}]
[--verbose={false|true}] [--watchdog={true|false}]
[instance-name]
```

## Description

The **start-local-instance** subcommand starts a Eclipse GlassFish instance on the host where the subcommand is run. This subcommand does not require the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured. You must run this command from the host where the instance resides.

The subcommand can start any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can start an instance that was created by using the [create-instance\(1\)](#) subcommand.

The **start-local-instance** subcommand does not contact the domain administration server (DAS) to determine the node on which the instance resides. To determine the node on which the instance resides, the subcommand searches the directory that contains the node directories. If multiple node directories exist, the node must be specified as an option of the subcommand.

This subcommand is supported in local mode. However, to synchronize the instance with the DAS, this subcommand must be run in remote mode.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--nodedir**

Specifies the directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is as-install/nodes.

**--node**

Specifies the node on which the instance resides. This option may be omitted only if the directory that the --nodedir option specifies contains only one node directory. Otherwise, this option is required.

**--debug****-d**

Specifies whether the instance is started with Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>) debugging enabled.

Possible values are as follows:

**true**

The instance is started with JPDA debugging enabled and the port number for JPDA debugging is displayed.

**false**

The instance is started with JPDA debugging disabled (default).

**--dry-run****-n**

Suppresses actual starting of the instance. Instead, start-local-instance displays the full command that would be used to start the instance, including all options. Reviewing this command can be useful when troubleshooting startup issues.

The default value is false.

**--sync**

The type of synchronization between the DAS and the instance's files when the instance is started.

Possible values are as follows:

**none**

The DAS does not synchronize the instance's files with any changes. This type of synchronization minimizes the time that is required to start the instance.

**normal**

The DAS synchronizes the instance with changes since the last synchronization as follows:

- For the config directory, the DAS synchronizes the instance with all changes.
- For the applications directory and docroot directory, only a change to a top-level subdirectory causes the DAS to synchronize all files under that subdirectory.

If a file below a top level subdirectory is changed without a change to a file in the top level subdirectory, full synchronization is required. In normal operation, files below the top level subdirectories of these directories are not changed. If an application is deployed and undeployed, full synchronization is not necessary to update the instance with the change.

This value is the default.

### **full**

The DAS synchronizes the instance with all of the instance's files, regardless of whether the files have changed since the last synchronization. This type of synchronization might delay the startup of the instance while the DAS updates all files in the instance's directories.



If the DAS is not running or is unreachable from the host where you are running this subcommand, do not set the `--sync` option to **full**. To perform a full synchronization, the subcommand removes the instance's cache. If the DAS cannot be contacted to replace the cache, the subcommand fails and the instance cannot be restarted until it is resynchronized with the DAS.

### **--verbose**

#### **-v**

Specifies whether detailed information about the instance is displayed in the console window where the subcommand is run.

Possible values are as follows:

#### **true**

Detailed startup messages and log messages about the instance are displayed in the console window where the subcommand is run. If the instance is later restarted by running the [restart-local-instance\(1\)](#) subcommand from a different console window, messages continue to be displayed in the original console window.

You can kill the Eclipse GlassFish process by typing **CTRL-C** in the console window.

You can kill the Eclipse GlassFish process and obtain a thread dump for the server by typing one of the following key combinations in the console window:

- **CTRL-\** on UNIX systems
- **CTRL-Break** on Windows systems

#### **false**

Detailed information is not displayed (default).

### **--watchdog**

#### **-w**

Specifies whether limited information about the instance is displayed in the console window where the subcommand is run. The `--watchdog` option is similar to `--verbose` but does not display the detailed startup messages and log messages. This option is useful when running the `asadmin` utility

in the background or with no attached console.

Possible values are as follows:

#### true

Limited information is displayed in the console window.

#### false

Limited information is not displayed in the console window (default).

## Operands

### instance-name

The name of the instance to start.

## Examples

### Example 1 Starting an Instance Locally

This example starts the instance `yml-i-sj01` on the host where the subcommand is run.

```
asadmin> start-local-instance --node sj01 yml-i-sj01
Waiting for the server to start .....
Successfully started the instance: yml-i-sj01
instance Location: /export/glassfish7/glassfish/nodes/sj01/yml-i-sj01
Log File: /export/glassfish7/glassfish/nodes/sj01/yml-i-sj01/logs/server.log
Admin Port: 24849
Command start-local-instance executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [restart-](#)

[instance\(1\)](#), [restart-local-instance\(1\)](#), [start-domain\(1\)](#), [start-instance\(1\)](#), [stop-domain\(1\)](#), [stop-instance\(1\)](#), [stop-local-instance\(1\)](#)

Java Platform Debugger Architecture (JPDA) (<http://www.oracle.com/technetwork/java/javase/tech/jpda-141715.html>)

# stop-cluster

Stops a Eclipse GlassFish cluster

## Synopsis

```
asadmin [asadmin-options] stop-cluster [--help]
[--verbose={false|true}]
[--kill={false|true}]
[--autohadboverride={true|false}]
cluster-name
```

## Description

The **stop-cluster** subcommand stops a Eclipse GlassFish cluster by stopping all running Eclipse GlassFish instances in the cluster.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --verbose

Specifies whether additional progress messages about the status of instances in the cluster are displayed while the cluster is being stopped.

Possible values are as follows:

#### true

Additional progress messages about the status of instances in the cluster are displayed.

#### false

No messages about the status of instances in the cluster are displayed.

#### --kill

Specifies whether each instance in the cluster is killed by using functionality of the operating system to terminate the instance process.

Possible values are as follows:

**false**

No instances are killed. The subcommand uses functionality of the Java platform to terminate each instance process (default).

**true**

Each instance is killed. The subcommand uses functionality of the operating system to terminate each instance process.

**--autohadboverride**

Do not specify this option. This option is retained for compatibility with earlier releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and displays a warning message that the option is ignored.

## Operands

**cluster-name**

The name of the cluster to stop.

## Examples

### Example 1 Stopping a Cluster

This example stops the cluster `pmdcluster`. Additional progress messages about the status of instances in the cluster are displayed while the cluster is being stopped.

```
asadmin> stop-cluster --verbose pmdcluster  
stop-instance pmd-i-sj01  
stop-instance pmd-i-sj02
```

The command `stop-instance` executed successfully for: pmd-i-sj01 pmd-i-sj02

Command `stop-cluster` executed successfully.

## Exit Status

**0**

command executed successfully

---

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-cluster\(1\)](#), [delete-cluster\(1\)](#), [list-clusters\(1\)](#), [start-cluster\(1\)](#)

# stop-database

Stops the Java DB

## Synopsis

```
asadmin [asadmin-options] stop-database [--help]
[--dbuser db-user]
[--dbhost host] [--dbport port-no]
```

## Description

The **stop-database** subcommand stops a process of the Java DB server. Java DB server is available for use with Eclipse GlassFish and is based upon Apache Derby. The database is typically started with the [start-database\(1\)](#) subcommand. A single host can have multiple database server processes running on different ports. The **stop-database** subcommand stops the database server process for the specified port only.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --dbuser

The user name of the Java DB user that is to stop the server process. This option is required only when Java DB user authentication is enabled.

If this option is omitted, no user is specified. By default, Java DB user authentication is disabled, so no user or password is required.

#### --dbhost

The host name or IP address of the Java DB server process. The default is the IP address 0.0.0.0, which denotes all network interfaces on the host where you run the **stop-database** subcommand.

#### --dbport

The port number where the Java DB server listens for client connections. The default is 1527.

# Examples

## Example 1 Stopping Java DB

This example stops Java DB on host host1 and port 5001.

```
asadmin> stop-database --dbhost host1 --dbport 5001
Connection obtained for host: host1, port number 5001.
Shutdown successful.
Command stop-database executed successfully.
```

## Exit Status

The exit status applies to errors in executing the `asadmin` utility. For information on database errors, see the `derby.log` file. This file is located in the directory you specify by using the `--dbhome` option when you run the `start-database` subcommand. If you did not specify `--dbhome`, the value of `DERBY_INSTALL` defaults to `as-install/javadb`.

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[start-database\(1\)](#)

["Administering Database Connectivity" in Eclipse GlassFish Administration Guide](#)

# stop-domain

Stops the Domain Administration Server of the specified domain

## Synopsis

```
asadmin [asadmin-options] stop-domain [--help]
[--domainmdir domainmdir]
[--force={true|false}] [--kill={false|true}]
[domain-name]
```

## Description

The **stop-domain** subcommand stops the Domain Administration Server (DAS) of the specified domain. If the domain directory is not specified, the domain in the default domains directory is stopped. If there are two or more domains in the domains directory, the domain-name operand must be specified.

This subcommand is supported in local or remote mode. If you specify a host name, the subcommand assumes you are operating in remote mode, which means you must correctly authenticate to the remote server. In local mode, you normally do not need to authenticate to the server as long as you are running the subcommand as the same user who started the server.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --domainmdir

Specifies the directory of the domain that is to be stopped. If specified, the path must be accessible in the file system. If not specified, the domain in the default as-install/**domains** directory is stopped.

#### --force

Specifies whether the domain is forcibly stopped immediately.

Possible values are as follows:

#### true

The domain is forcibly stopped immediately (default).

**false**

The subcommand waits until all threads that are associated with the domain are exited before stopping the domain.

**--kill**

Specifies whether the domain is killed by using functionality of the operating system to terminate the domain process.

Possible values are as follows:

**false**

The domain is not killed. The subcommand uses functionality of the Java platform to terminate the domain process (default).

**true**

The domain is killed. The subcommand uses functionality of the operating system to terminate the domain process.

## Operands

**domain-name**

The name of the domain you want to stop. Default is the name specified during installation, usually `domain1`.

## Examples

### Example 1 Stopping a Domain

This example stops the domain named `sampleDomain` in the default domains directory.

```
asadmin> stop-domain sampleDomain
Waiting for the domain to stop .....
Command stop-domain executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[delete-domain\(1\)](#), [list-domains\(1\)](#), [restart-domain\(1\)](#), [start-domain\(1\)](#)

# stop-instance

Stops a running Eclipse GlassFish instance

## Synopsis

```
asadmin [asadmin-options] stop-instance [--help]
[--force={false|true}] [--kill={false|true}]
instance-name
```

## Description

The **stop-instance** subcommand stops a running Eclipse GlassFish instance.

The subcommand can stop any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can stop an instance that was created by using the [create-local-instance\(1\)](#) subcommand.

This command is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --force

Specifies whether the instance is forcibly stopped immediately.

Possible values are as follows:

##### true

The instance is forcibly stopped immediately (default).

##### false

The subcommand waits until all threads that are associated with the instance are exited before stopping the instance.

#### --kill

Specifies whether the instance is killed by using functionality of the operating system to terminate

the instance process.

Possible values are as follows:

#### false

The instance is not killed. The subcommand uses functionality of the Java platform to terminate the instance process (default).

#### true

The instance is killed. The subcommand uses functionality of the operating system to terminate the instance process.

## Operands

### instance-name

This is the name of the Eclipse GlassFish instance to stop.

## Examples

This example stops the Eclipse GlassFish instance `yml-i-sj01`.

### Example 1 Stopping a Eclipse GlassFish Instance

```
asadmin> stop-instance yml-i-sj01
The instance, yml-i-sj01, was stopped.
```

Command stop-instance executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [start-](#)

---

[domain\(1\)](#), [start-instance\(1\)](#), [start-local-instance\(1\)](#), [stop-domain\(1\)](#), [stop-local-instance\(1\)](#)

# stop-local-instance

Stops a Eclipse GlassFish instance on the machine where the subcommand is run

## Synopsis

```
asadmin [asadmin-options] stop-local-instance [--help]
[--nodedir node-dir] [--node node]
[--force={true|false}] [--kill={false|true}]
[instance-name]
```

## Description

The **stop-local-instance** subcommand stops a Eclipse GlassFish instance on the machine where the subcommand is run. This subcommand does not require secure shell (SSH) to be configured. You must run this command from the machine where the instance resides.

The subcommand can stop any Eclipse GlassFish instance, regardless of how the instance was created. For example, this subcommand can stop an instance that was created by using the [create-instance\(1\)](#) subcommand.

The **stop-local-instance** subcommand does not contact the DAS to determine the node on which the instance resides. To determine the node on which the instance resides, the subcommand searches the directory that contains the node directories. If multiple node directories exist, the node must be specified as an option of the subcommand.

This subcommand is supported in local mode.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--nodedir**

Specifies the directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is `as-install/nodes`.

**--node**

Specifies the node on which the instance resides. This option may be omitted only if the directory that the `--nodedir` option specifies contains only one node directory. Otherwise, this option is required.

**--force**

Specifies whether the instance is forcibly stopped immediately.

Possible values are as follows:

**true**

The instance is forcibly stopped immediately (default).

**false**

The subcommand waits until all threads that are associated with the instance are exited before stopping the instance.

**--kill**

Specifies whether the instance is killed by using functionality of the operating system to terminate the instance process.

Possible values are as follows:

**false**

The instance is not killed. The subcommand uses functionality of the Java platform to terminate the instance process (default).

**true**

The instance is killed. The subcommand uses functionality of the operating system to terminate the instance process.

# Operands

**instance-name**

The name of the instance to stop.

# Examples

## Example 1 Stopping an Instance Locally

This example stops the instance `yml-i-sj01` on the machine where the subcommand is run.

```
asadmin> stop-local-instance --node sj01 yml-i-sj01
Waiting for the instance to stop ...
Command stop-local-instance executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-instance\(1\)](#), [create-local-instance\(1\)](#), [delete-instance\(1\)](#), [delete-local-instance\(1\)](#), [start-instance\(1\)](#), [start-local-instance\(1\)](#), [stop-instance\(1\)](#)

# undeploy

Removes a deployed component

## Synopsis

```
asadmin [asadmin-options] undeploy [--help]
[--target target] [--droptables={true|false}]
[--cascade={false|true}] name
```

## Description

The **undeploy** subcommand uninstalls a deployed application or module and removes it from the repository.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --cascade

If set to **true**, deletes all the connection pools and connector resources associated with the resource adapter being undeployed. If set to **false**, the undeploy fails if any pools and resources are still associated with the resource adapter. Then, either those pools and resources must be deleted explicitly, or the option must be set to **true**. If the option is set to **false**, and if there are no pools and resources still associated with the resource adapter, the resource adapter is undeployed. This option is applicable to connectors (resource adapters) and applications. Default value is false.

#### --droptables

If set to true, drops the tables that the application created by using CMP beans during deployment. If set to false, tables are not dropped. If not specified, the value of the **drop-tables-at-deploy** entry in the **cmp-resource** element of the **glassfish-ejb-jar.xml** file determines whether or not tables are dropped. Default value is true.

#### --target

Specifies the target from which you are undeploying. Valid values are:

**server**

Undeploys the component from the default server instance **server** and is the default value.

**domain**

Undeploys the component from the domain.

**cluster\_name**

Undeploys the component from every server instance in the cluster.

**instance\_name**

Undeploys the component from a particular stand-alone server instance.

## Operands

**name**

Name of the deployed component.

The name can include an optional version identifier, which follows the name and is separated from the name by a colon (:). The version identifier must begin with a letter or number. It can contain alphanumeric characters plus underscore (\_), dash (-), and period (.) characters. To delete multiple versions, you can use an asterisk (\*) as a wildcard character. For more information about module and application versions, see "[Module and Application Versions](#)" in Eclipse GlassFish Application Deployment Guide.

## Examples

### Example 1 Undeploying an Enterprise Application

This example undeploys an enterprise application named **Cart.ear**.

```
asadmin> undeploy Cart
Command undeploy executed successfully.
```

### Example 2 Undeploying an Enterprise Bean With Container-Managed Persistence (CMP)

This example undeploys a CMP bean named **myejb** and drops the corresponding database tables.

```
asadmin> undeploy --droptables=true myejb
Command undeploy executed successfully.
```

## Example 3 Undeploying a Connector (Resource Adapter)

This example undeploys the connector module named `jdbcrea` and performs a cascading delete to remove the associated resources and connection pools.

```
asadmin> undeploy --cascade=true jdbcrea
Command undeploy executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[deploy\(1\)](#), [list-components\(1\)](#), [redeploy\(1\)](#)

[Eclipse GlassFish Application Deployment Guide](#)

# unfreeze-transaction-service

Resumes all suspended transactions

## Synopsis

```
asadmin [asadmin-options] unfreeze-transaction-service [--help]
[--target target]
```

## Description

The **unfreeze-transaction-service** subcommand restarts the transaction subsystem and resumes all in-flight transactions. Invoke this subcommand on an already frozen transaction subsystem. This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

**--target**

This option specifies the target on which you are unfreezing the transaction service. Valid values are:

**server**

Unfreezes the transaction service for the default server instance **server** and is the default value.

**configuration\_name**

Unfreezes the transaction service for all server instances that use the named configuration.

**cluster\_name**

Unfreezes the transaction service for every server instance in the cluster.

**instance\_name**

Unfreezes the transaction service for a particular server instance.

# Examples

## Example 1 Using unfreeze-transaction-service

```
% asadmin unfreeze-transaction-service  
Command unfreeze-transaction-service executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[freeze-transaction-service\(1\)](#), [recover-transactions\(1\)](#), [rollback-transaction\(1\)](#)

"[Administering Transactions](#)" in Eclipse GlassFish Administration Guide

"[Transactions](#)" in The Jakarta EE Tutorial

# uninstall-node

Uninstalls Eclipse GlassFish software from specified hosts

## Synopsis

```
asadmin [asadmin-options] uninstall-node [--help]
[--installdir as-install-parent]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile]
[--force={false|true}]
host-list
```

## Description

The `uninstall-node` subcommand uninstalls Eclipse GlassFish software from the hosts that are specified as the operand of the subcommand. This subcommand requires secure shell (SSH) to be configured on the host where the subcommand is run and on each host where the Eclipse GlassFish software is being uninstalled.



This subcommand is equivalent to the `uninstall-node-ssh(1)` subcommand. To uninstall Eclipse GlassFish software on hosts that use the Distributed Component Object Model (DCOM) remote protocol, use the `uninstall-node-dcom(1)` subcommand.

By default, if any node except the predefined node `localhost`-domain resides on any host from which Eclipse GlassFish software is being uninstalled, the subcommand fails. To uninstall the Eclipse GlassFish software from a host on which user-defined nodes reside, set the `--force` option to `true`. If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

If a file under the parent of the base installation directory is open, the subcommand fails.

If multiple hosts are specified, the configuration of the following items must be the same on all hosts:

- Parent of the base installation directory for the Eclipse GlassFish software
- SSH port
- SSH user
- SSH key file

The subcommand does not modify the configuration of the domain administration server (DAS).

This subcommand is supported in local mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

-?

Displays the help text for the subcommand.

### --installdir

The absolute path to the parent of the base installation directory where the Eclipse GlassFish software is installed on each host, for example, `/export/glassfish7/`.

The user that is running this subcommand must have write access to the specified directory. Otherwise, an error occurs.

The specified directory must contain the installation of the Eclipse GlassFish software on the host. Otherwise, an error occurs.

The default is the parent of the base installation directory of the Eclipse GlassFish software on the host where this subcommand is run.

### --sshport

The port to use for SSH connections to the host where the Eclipse GlassFish software is to be uninstalled. The default is 22.

### --sshuser

The user on the host where the Eclipse GlassFish software is to be uninstalled that is to run the process for connecting through SSH to the host. The default is the user that is running this subcommand. To ensure that the DAS can read this user's SSH private key file, specify the user that is running the DAS process.

### --sshkeyfile

The absolute path to the SSH private key file for user that the `--sshuser` option specifies. This file is used for authentication to the `sshd` daemon on the host.

The user that is running this subcommand must be able to reach the path to the key file and read the key file.

The default is a key file in the user's `.ssh` directory. If multiple key files are found, the subcommand uses the following order of preference:

1. `id_rsa`
2. `id_dsa`
3. `identity`

### --force

Specifies whether the subcommand uninstalls the Eclipse GlassFish software from a host even if a user-defined node resides on the host. Possible values are as follows:

**false**

If a user-defined node resides on a host, the software is not uninstalled and the subcommand fails (default).

If the `--force` option is `false`, the subcommand removes only the Eclipse GlassFish software files. Other content if the parent of the base installation directory, such as configuration files, are not removed.

**true**

The subcommand uninstalls the Eclipse GlassFish software from the host even if a user-defined node resides on the host.

If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

## Operands

**host-list**

A space-separated list of the names of the hosts from which the Eclipse GlassFish software is to be uninstalled.

## Examples

### Example 1 Uninstalling Eclipse GlassFish Software From the Default Location

This example uninstalls Eclipse GlassFish software on the hosts `sj03.example.com` and `sj04.example.com` from the default location.

```
asadmin> uninstall-node sj03 sj04
Successfully connected to gfuser@sj03.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Successfully connected to gfuser@sj04.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Command uninstall-node executed successfully.
```

### Example 2 Forcibly Uninstalling Eclipse GlassFish Software

This example uninstalls Eclipse GlassFish software on the host `sj02.example.com`.

The software is uninstalled even if a user-defined node resides on the host. The entire content of the `/export/glassfish7` directory is removed.

Some lines of output are omitted from this example for readability.

```
asadmin> uninstall-node --force --installdir /export/glassfish7 sj02.example.com
Successfully connected to gfuser@sj02.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Force removing file /export/glassfish7/mq/lib/help/en/add_overrides.htm
Force removing file /export/glassfish7/mq/lib/help/en/add_connfact.htm
...
Force removing directory /export/glassfish7/glassfish/lib/appclient
Force removing directory /export/glassfish7/glassfish/lib
Force removing directory /export/glassfish7/glassfish
Command uninstall-node executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#)

# uninstall-node-dcom

Uninstalls Eclipse GlassFish software from specified DCOM-enabled hosts

## Synopsis

```
asadmin [asadmin-options] uninstall-node-dcom [--help]
[--installdir as-install-parent]
[--windowsuser windows-user] [--windowsdomain windows-domain]
[--force={false|true}]
host-list
```

## Description

The **uninstall-node-dcom** subcommand uninstalls Eclipse GlassFish software from the hosts that are specified as the operand of the subcommand. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol to be configured on the host where the subcommand is run and on each host where the Eclipse GlassFish software is being uninstalled.



To uninstall Eclipse GlassFish software on hosts that use secure shell (SSH), use the [uninstall-node-ssh\(1\)](#) subcommand.

By default, if any node except the predefined node `localhost`-domain resides on any host from which Eclipse GlassFish software is being uninstalled, the subcommand fails. To uninstall the Eclipse GlassFish software from a host on which user-defined nodes reside, set the `--force` option to `true`. If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

If a file under the parent of the base installation directory is open, the subcommand fails.

If multiple hosts are specified, the configuration of the following items must be the same on all hosts:

- Parent of the base installation directory for the Eclipse GlassFish software
- Windows user
- Windows domain

The subcommand does not modify the configuration of the domain administration server (DAS).

This subcommand is supported in local mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

`-?`

Displays the help text for the subcommand.

### --installdir

The absolute path to the parent of the base installation directory where the Eclipse GlassFish software is installed on each host, for example, `C:\glassfish7`.

The user that is running this subcommand must have write access to the specified directory. Otherwise, an error occurs.

The specified directory must contain the installation of the Eclipse GlassFish software on the host. Otherwise, an error occurs.

The default is the parent of the base installation directory of the Eclipse GlassFish software on the host where this subcommand is run.

### --windowsuser

`-W`

The user on this node's host that is to run the process for connecting to the host through DCOM. The default is the user that is running the DAS process.

### --windowsdomain

`-d`

The name of the Windows domain that contains the user that the `--windowsuser` option specifies. The default is the name of the host on which the subcommand is run.

### --force

Specifies whether the subcommand uninstalls the Eclipse GlassFish software from a host even if a user-defined node resides on the host. Possible values are as follows:

#### false

If a user-defined node resides on a host, the software is not uninstalled and the subcommand fails (default).

If the `--force` option is `false`, the subcommand removes only the Eclipse GlassFish software files. Other content in the parent of the base installation directory, such as configuration files, are not removed.

#### true

The subcommand uninstalls the Eclipse GlassFish software from the host even if a user-defined node resides on the host.

If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

## Operands

### host-list

A space-separated list of the names of the hosts from which the Eclipse GlassFish software is to be uninstalled.

## Examples

### Example 1 Uninstalling Eclipse GlassFish Software From the Default Location

This example uninstalls Eclipse GlassFish software on the hosts `wpmdl1.example.com` and `wpmdl2.example.com` from the default location.

```
asadmin> uninstall-node-dcom wpmdl1 wpmdl2
Command uninstall-node-dcom executed successfully.
```

### Example 2 Forcibly Uninstalling Eclipse GlassFish Software

This example uninstalls Eclipse GlassFish software on the host `xkyd.example.com`.

The software is uninstalled even if a user-defined node resides on the host. The entire content of the `C:\glassfish7` directory is removed.

```
asadmin> uninstall-node-dcom --force --installdir C:\glassfish7 xkyd.example.com
Command uninstall-node-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

---

## See Also

[asadmin\(1M\)](#)

[install-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#)

# uninstall-node-ssh

Uninstalls Eclipse GlassFish software from specified SSH-enabled hosts

## Synopsis

```
asadmin [asadmin-options] uninstall-node-ssh [--help]
[--installdir as-install-parent]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile]
[--force={false|true}]
host-list
```

## Description

The [uninstall-node-ssh](#) subcommand uninstalls Eclipse GlassFish software from the hosts that are specified as the operand of the subcommand. This subcommand requires secure shell (SSH) to be configured on the host where the subcommand is run and on each host where the Eclipse GlassFish software is being uninstalled.



This subcommand is equivalent to the [uninstall-node\(1\)](#) subcommand. To uninstall Eclipse GlassFish software from hosts that use the Distributed Component Object Model (DCOM) remote protocol, use the [uninstall-node-dcom\(1\)](#) subcommand.

By default, if any node except the predefined node `localhost`-domain resides on any host from which Eclipse GlassFish software is being uninstalled, the subcommand fails. To uninstall the Eclipse GlassFish software from a host on which user-defined nodes reside, set the `--force` option to `true`. If the `--force` option is `true`, the subcommand removes the entire content of the parent of the base installation directory.

If a file under the parent of the base installation directory is open, the subcommand fails.

If multiple hosts are specified, the configuration of the following items must be the same on all hosts:

- Parent of the base installation directory for the Eclipse GlassFish software
- SSH port
- SSH user
- SSH key file

The subcommand does not modify the configuration of the domain administration server (DAS).

This subcommand is supported in local mode only.

# Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

-?

Displays the help text for the subcommand.

### --installdir

The absolute path to the parent of the base installation directory where the Eclipse GlassFish software is installed on each host, for example, `/export/glassfish7/`.

The user that is running this subcommand must have write access to the specified directory. Otherwise, an error occurs.

The specified directory must contain the installation of the Eclipse GlassFish software on the host. Otherwise, an error occurs.

The default is the parent of the base installation directory of the Eclipse GlassFish software on the host where this subcommand is run.

### --sshport

The port to use for SSH connections to the host where the Eclipse GlassFish software is to be uninstalled. The default is 22.

### --sshuser

The user on the host where the Eclipse GlassFish software is to be uninstalled that is to run the process for connecting through SSH to the host. The default is the user that is running this subcommand. To ensure that the DAS can read this user's SSH private key file, specify the user that is running the DAS process.

### --sshkeyfile

The absolute path to the SSH private key file for user that the `--sshuser` option specifies. This file is used for authentication to the `sshd` daemon on the host.

The user that is running this subcommand must be able to reach the path to the key file and read the key file.

The default is a key file in the user's `.ssh` directory. If multiple key files are found, the subcommand uses the following order of preference:

1. `id_rsa`
2. `id_dsa`
3. `identity`

### --force

Specifies whether the subcommand uninstalls the Eclipse GlassFish software from a host even if a user-defined node resides on the host. Possible values are as follows:

**false**

If a user-defined node resides on a host, the software is not uninstalled and the subcommand fails (default).

If the `--force` option is **false**, the subcommand removes only the Eclipse GlassFish software files. Other content if the parent of the base installation directory, such as configuration files, are not removed.

**true**

The subcommand uninstalls the Eclipse GlassFish software from the host even if a user-defined node resides on the host.

If the `--force` option is **true**, the subcommand removes the entire content of the parent of the base installation directory.

## Operands

**host-list**

A space-separated list of the names of the hosts from which the Eclipse GlassFish software is to be uninstalled.

## Examples

### Example 1 Uninstalling Eclipse GlassFish Software From the Default Location

This example uninstalls Eclipse GlassFish software on the hosts `sj03.example.com` and `sj04.example.com` from the default location.

```
asadmin> uninstall-node-ssh sj03 sj04
Successfully connected to gfuser@sj03.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Successfully connected to gfuser@sj04.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Command uninstall-node-ssh executed successfully.
```

### Example 2 Forcibly Uninstalling Eclipse GlassFish Software

This example uninstalls Eclipse GlassFish software on the host `sj02.example.com`.

The software is uninstalled even if a user-defined node resides on the host. The entire content of the `/export/glassfish7` directory is removed.

Some lines of output are omitted from this example for readability.

```
asadmin> uninstall-node-ssh --force --installdir /export/glassfish7 sj02.example.com
Successfully connected to gfuser@sj02.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Force removing file /export/glassfish7/mq/lib/help/en/add_overrides.htm
Force removing file /export/glassfish7/mq/lib/help/en/add_connfact.htm
...
Force removing directory /export/glassfish7/glassfish/lib/appclient
Force removing directory /export/glassfish7/glassfish/lib
Force removing directory /export/glassfish7/glassfish
Command uninstall-node-ssh executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[install-node\(1\)](#), [install-node-ssh\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#)

# unset

Removes one or more variables from the multimode environment

## Synopsis

```
asadmin [asadmin-options] unset [--help]  
variable-list
```

## Description

The `unset` subcommand removes one or more environment variables that are set for the multimode environment. After removal, the variables and their associated values no longer apply to the multimode environment.

To list the environment variables that are set, use the `export` subcommand without options. If the `export` subcommand lists no environment variables, no environment variables are set.

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

### -?

Displays the help text for the subcommand.

## Operands

### variable-list

A space-separated list of the environment variables to remove.

## Examples

### Example 1 Listing the Environment Variables That Are Set

This example uses the `export` subcommand to list the environment variables that have been set.

```
asadmin> export  
AS_ADMIN_USER = admin  
AS_ADMIN_HOST = bluestar  
AS_ADMIN_PREFIX = server1.jms-service  
AS_ADMIN_PORT = 8000  
Command export executed successfully
```

## Example 2 Removing an Environment Variable

This example removes the `AS_ADMIN_PREFIX` environment variable.

```
asadmin> unset AS_ADMIN_PREFIX  
Command unset executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[export\(1\)](#), [multimode\(1\)](#)

# unset-web-context-param

Unsets a servlet context-initialization parameter of a deployed web application or module

## Synopsis

```
asadmin [asadmin-options] unset-web-context-param [--help]
--name=context-param-name application-name[/module]
```

## Description

The `unset-web-context-param` subcommand unsets a servlet context-initialization parameter of one of the following items:

- A deployed web application
- A web module in a deployed Java Platform, Enterprise Edition (Jakarta EE) application

When a parameter is unset, its value reverts to the value, if any, that is set in the application's deployment descriptor.

The application must already be deployed. Otherwise, an error occurs.

The parameter must have previously been set by using the `set-web-context-param` subcommand. Otherwise, an error occurs.



Do not use the `unset-web-context-param` subcommand to change the value of a servlet context-initialization parameter that is set in an application's deployment descriptor. Instead, use the `set-web-context-param(1)` subcommand for this purpose.

This subcommand enables you to change the configuration of a deployed application without the need to modify the application's deployment descriptors and repackage and redeploy the application.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--name**

The name of the servlet context-initialization parameter that is to be unset. This parameter must have previously been set by using the `set-web-context-param` subcommand. Otherwise, an error occurs.

# Operands

**application-name**

The name of the application. This name can be obtained from the Administration Console or by using the `list-applications(1)` subcommand.

The application must already be deployed. Otherwise, an error occurs.

**module**

The relative path to the module within the application's enterprise archive (EAR) file. The path to the module is specified in the `module` element of the application's `application.xml` file.

`module` is required only if the servlet context-initialization parameter applies to a web module of a Jakarta EE application. If specified, `module` must follow `application-name`, separated by a slash (`/`).

For example, the `application.xml` file for the `myApp` application might specify the following web module:

```
<module>
  <web>
    <web-uri>myWebModule.war</web-uri>
  </web>
</module>
```

The module would be specified as the operand of this command as `myApp/myWebModule.war`.

# Examples

## Example 1 Unsetting a Servlet Context-Initialization Parameter for a Web Application

This example unsets the servlet context-initialization parameter `javax.faces.STATE_SAVING_METHOD` of the web application `basic-ezcomp`. The parameter reverts to the value, if any, that is defined in the application's deployment descriptor.

```
asadmin> unset-web-context-param  
--name=javax.faces.STATE_SAVING_METHOD basic-ezcomp
```

Command unset-web-context-param executed successfully.

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [list-web-context-param\(1\)](#), [set-web-context-param\(1\)](#)

# unset-web-env-entry

Unsets an environment entry for a deployed web application or module

## Synopsis

```
asadmin [asadmin-options] unset-web-env-entry [--help]
--name=env-entry-name application-name[/module]
```

## Description

The `unset-web-env-entry` subcommand unsets an environment entry for one of the following items:

- A deployed web application
- A web module in a deployed Java Platform, Enterprise Edition (Jakarta EE) application

When an entry is unset, its value reverts to the value, if any, that is set in the application's deployment descriptor.

The application must already be deployed. Otherwise, an error occurs.

The entry must have previously been set by using the `set-web-env-entry(1)` subcommand. Otherwise, an error occurs.



Do not use the `unset-web-env-entry` subcommand to change the value of an environment entry that is set in an application's deployment descriptor. Instead, use the `set-web-env-entry` subcommand for this purpose.

This subcommand enables you to change the configuration of a deployed application without the need to modify the application's deployment descriptors and repackage and redeploy the application.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the `asadmin(1M)` help page.

`--help`

`-?`

Displays the help text for the subcommand.

**--name**

The name of the environment entry that is to be unset. The name is a JNDI name relative to the `java:comp/env` context. The name must be unique within a deployment component. This entry must have previously been set by using the `set-web-env-entry` subcommand. Otherwise, an error occurs.

## Operands

### application-name

The name of the application. This name can be obtained from the Administration Console or by using the `list-applications(1)` subcommand.

The application must already be deployed. Otherwise, an error occurs.

### module

The relative path to the module within the application's enterprise archive (EAR) file. The path to the module is specified in the `module` element of the application's `application.xml` file.

module is required only if the environment entry applies to a web module of a Jakarta EE application. If specified, module must follow application-name, separated by a slash (/).

For example, the `application.xml` file for the `myApp` application might specify the following web module:

```
<module>
  <web>
    <web-uri>myWebModule.war</web-uri>
  </web>
</module>
```

The module would be specified as the operand of this command as `myApp/myWebModule.war`.

## Examples

### Example 1 Unsetting an Environment Entry for a Web Application

This example unsets the environment entry `Hello User` of the web application `hello`. The entry reverts to the value, if any, that is defined in the application's deployment descriptor.

```
asadmin> unset-web-env-entry --name="Hello User" hello
```

```
Command unset-web-env-entry executed successfully.
```

---

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[list-applications\(1\)](#), [list-web-env-entry\(1\)](#), [set-web-env-entry\(1\)](#)

# update-connector-security-map

Modifies a security map for the specified connector connection pool

## Synopsis

```
asadmin [asadmin-options] update-connector-security-map [--help]
--poolname connector_connection_pool_name
[--addprincipals principal_name1[,principal_name2]*]
[--addusergroups user_group1[,user_group2]*]
[--removeprincipals principal_name1[,principal_name2]*]
[--removeusergroups user_group1[,user_group2]*]
[--mappedusername username]
mapname
```

## Description

The **update-connector-security-map** subcommand modifies a security map for the specified connector connection pool.

For this subcommand to succeed, you must have first created a connector connection pool using the **create-connector-connection-pool** subcommand.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --poolname

Specifies the name of the connector connection pool to which the security map that is to be updated belongs.

### --addprincipals

Specifies a comma-separated list of EIS-specific principals to be added. Use either the **--addprincipals** or **--addusergroups** options, but not both in the same command.

**--addusergroups**

Specifies a comma-separated list of EIS user groups to be added. Use either the **--addprincipals** or **--addusergroups** options, but not both in the same command.

**--removeprincipals**

Specifies a comma-separated list of EIS-specific principals to be removed.

**--removeusergroups**

Specifies a comma-separated list of EIS user groups to be removed.

**--mappedusername**

Specifies the EIS username.

## Operands

**mapname**

The name of the security map to be updated.

## Examples

### Example 1 Updating a Connector Security Map

This example adds principals to the existing security map named **securityMap1**.

```
asadmin> update-connector-security-map --poolname connector-pool1  
--addprincipals principal1,principal2 securityMap1  
Command update-connector-security-map executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-security-map\(1\)](#), [delete-connector-security-map\(1\)](#), [list-connector-security-maps\(1\)](#)

# update-connector-work-security-map

Modifies a work security map for the specified resource adapter

## Synopsis

```
asadmin [asadmin-options] update-connector-work-security-map [--help]
--raname raname
[--addprincipals eis-principal1=server-principal1[, eis-principal2=server-principal2]*]
[--addgroups eis-group1=server-group1[, eis-group2=server-group2]*]
[--removeprincipals eis-principal1[,eis-principal2]*]
[--removegroups eis-group1[, eis-group2]*]
mapname
```

## Description

The `update-connector-work-security-map` subcommand modifies a security map for the specified resource adapter.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

`-?`

Displays the help text for the subcommand.

#### --addgroups

Specifies a comma-separated list of EIS groups to be added. Use either the `--addprincipals` option or the `--addgroups` option, but not both.

#### --addprincipals

Specifies a comma-separated list of EIS-specific principals to be added. Use either the `--addprincipals` option or the `--addgroups` option, but not both.

#### --removegroups

Specifies a comma-separated list of EIS groups to be removed.

**--removeprincipals**

Specifies a comma-separated list of EIS-specific principals to be removed.

**--rname**

Indicates the connector module name with which the work security map is associated.

## Operands

**mapname**

The name of the work security map to be updated.

## Examples

### Example 1 Updating a Connector Work Security Map

This example updates `workSecurityMap2` by removing `eis-group-2`.

```
asadmin> update-connector-work-security-map  
--rname my-resource-adapter --removegroups eis-group-2 workSecurityMap2  
Command update-connector-work-security-map executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-connector-work-security-map\(1\)](#), [delete-connector-work-security-map\(1\)](#), [list-connector-work-security-maps\(1\)](#)

# update-file-user

Updates a current file user as specified

## Synopsis

```
asadmin [asadmin-options] update-file-user [--help]
[--groups user_groups[:user_groups]*]
[--target target]
[--authrealmname authrealm_name]
username
```

## Description

The `update-file-user` subcommand updates an existing entry in the keyfile using the specified user name, password and groups. Multiple groups can be entered by separating them, with a colon (:).

If a new password is not provided, this subcommand fails if secure administration is enabled and the user being updated is an administrative user.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

-?

Displays the help text for the subcommand.

#### --groups

This is the name of the group to which the file user belongs.

#### --authrealmname

Name of the authentication realm where the user to be updated can be found.

#### --target

This option helps specify the target on which you are updating a file user. Valid values are:

#### server

Updates the file user in the default server instance. This is the default value.

**cluster\_name**

Updates the file user on every server instance in the cluster.

**instance\_name**

Updates the file user on a specified sever instance.

## Operands

**username**

This is the name of the file user to be updated.

## Examples

### Example 1 Updating a User's Information in a File Realm

The following example updates information for a file realm user named `sample_user`.

```
asadmin> update-file-user  
--groups staff:manager:engineer sample_user  
Command update-file-user executed successfully
```

## Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[create-file-user\(1\)](#), [delete-file-user\(1\)](#), [list-file-groups\(1\)](#), [list-file-users\(1\)](#)

# update-node-config

Updates the configuration data of a node

## Synopsis

```
asadmin [asadmin-options] update-node-config [--help]
[--nodehost node-host]
[--installdir as-install-parent] [--nodedir node-dir]
node-name
```

## Description

The [update-node-config](#) subcommand updates the configuration data of a node.

This subcommand can update any node, regardless of whether the node is enabled for remote communication. If a node that is enabled for remote communication is updated, the node is not enabled for remote communication after the update.

Options of this subcommand specify the new values of the node's configuration data. The default for these options is to leave the existing value unchanged.

This subcommand does not require the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be configured to update the node. You may run this subcommand from any host that can contact the DAS.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the [asadmin](#) utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

### --nodehost

The name of the host that the node is to represent after the node is updated.

### --installdir

The full path to the parent of the base installation directory of the Eclipse GlassFish software on the host, for example, [/export/glassfish7](#).

**--nodedir**

The path to the directory that is to contain Eclipse GlassFish instances that are created on the node. If a relative path is specified, the path is relative to the as-install directory, where as-install is the base installation directory of the Eclipse GlassFish software on the host.

## Operands

**node-name**

The name of the node to update. The node must exist. Otherwise, an error occurs.

## Examples

### Example 1 Updating the Host That a Node Represents

This example updates the host that the node `sj04` represents to `hsj04`.

```
asadmin> update-node-config --nodehost hsj04 sj04
Command update-node-config executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-nodes\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-dcom\(1\)](#), [update-node-ssh\(1\)](#)

# update-node-dcom

Updates the configuration data of a node

## Synopsis

```
asadmin [asadmin-options] update-node-dcom [--help]
[--nodehost node-host]
[--installdir as-install-parent] [--nodedir node-dir]
[--windowsuser windows-user] [--windowsdomain windows-domain]
[--force={false|true}]
node-name
```

## Description

The **update-node-dcom** subcommand updates the configuration data of a node. This subcommand requires the Distributed Component Object Model (DCOM) remote protocol to be configured on the host where the domain administration server (DAS) is running and on the host where the node resides. The DCOM protocol is available only on Windows systems. You may run this subcommand from any host that can contact the DAS.

This subcommand can update any node, regardless of whether the node is enabled for remote communication. If the node is not enabled for remote communication, the subcommand enables DCOM communication for the node and updates any other specified configuration data.

Options of this subcommand specify the new values of the node's configuration data. The default for most options is to leave the existing value unchanged. However, if this subcommand is run to enable DCOM communication for a node, default values are applied if any of the following options is omitted:

- **--windowsuser**
- **--windowsdomain**

By default, the subcommand fails and the node is not updated if the DAS cannot contact the node's host through DCOM. To force the node to be updated even if the host cannot be contacted through DCOM, set the **--force** option to **true**.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--nodehost**

The name of the host that the node is to represent after the node is updated.

**--installdir**

The full path to the parent of the base installation directory of the Eclipse GlassFish software on the host, for example, `/export/glassfish7/`.

**--nodedir**

The path to the directory that is to contain Eclipse GlassFish instances that are created on the node. If a relative path is specified, the path is relative to the as-install directory, where as-install is the base installation directory of the Eclipse GlassFish software on the host.

**--windowsuser****-w**

The user on this node's host that is to run the process for connecting to the host through DCOM. The default depends on whether this subcommand is run to enable DCOM communication for the node:

- If the node is already enabled for communication over DCOM, the default is to leave the user unchanged.
- If this subcommand is run to enable DCOM communication for the node, the default is the user that is running the DAS process.

If the `--nodehost` option is set to `localhost`, the `--windowsuser` option is ignored.

**--windowsdomain****-d**

The name of the Windows domain that contains the user that the `--windowsuser` option specifies. The default depends on whether this subcommand is run to enable DCOM communication for the node:

- If the node is already enabled for communication over DCOM, the default is to leave the domain unchanged.
- If this subcommand is run to enable DCOM communication for the node, the default is the name of the host on which the subcommand is run.

**--force**

Specifies whether the node is updated even if validation of the node's parameters fails. To validate a node's parameters, the DAS must be able to contact the node's host through DCOM. Possible values are as follows:

**false**

The node is not updated if validation of the node's parameters fails (default).

**true**

The node is updated even if validation of the node's parameters fails.

## Operands

**node-name**

The name of the node to update. The node must exist. Otherwise, an error occurs.

## Examples

### Example 1 Updating the Host That a Node Represents

This example updates the host that the node `wpmdl1` represents to `wj01`.

```
asadmin> update-node-dcom --nodehost wj01 wpmdl1
Command update-node-dcom executed successfully.
```

### Example 2 Forcing the Update of a Node

This example forces the update of the node `xkyd` to enable the node to communicate over DCOM.

```
asadmin> update-node-dcom --force xkyd
Warning: some parameters appear to be invalid.
Could not find a remote Glassfish installation on host: xkyd.example.com at
C:\glassfish7\glassfish
Continuing with node update due to use of --force.
Command update-node-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-config\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-nodes\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-config\(1\)](#), [update-node-ssh\(1\)](#)

# update-node-ssh

Updates the configuration data of a node

## Synopsis

```
asadmin [asadmin-options] update-node-ssh [--help]
[--nodehost node-host]
[--installdir as-install-parent] [--nodedir node-dir]
[--sshport ssh-port] [--sshuser ssh-user]
[--sshkeyfile ssh-keyfile]
[--force={false|true}]
node-name
```

## Description

The `update-node-ssh` subcommand updates the configuration data of a node. This subcommand requires secure shell (SSH) to be configured on the machine where the domain administration server (DAS) is running and on the machine where the node resides. You may run this subcommand from any machine that can contact the DAS.

This subcommand can update any node, regardless of whether the node is enabled for remote communication. If the node is not enabled for remote communication, the subcommand enables SSH communication for the node and updates any other specified configuration data.

Options of this subcommand specify the new values of the node's configuration data. The default for most options is to leave the existing value unchanged. However, if this subcommand is run to enable SSH communication for a node, default values are applied if any of the following options is omitted:

- `--sshport`
- `--sshuser`
- `--sshkeyfile`

By default, the subcommand fails and the node is not updated if the DAS cannot contact the node's host through SSH. To force the node to be updated even if the host cannot be contacted through SSH, set the `--force` option to `true`.

This subcommand is supported in remote mode only.

## Options

## asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

### --help

-?

Displays the help text for the subcommand.

### --nodehost

The name of the host that the node is to represent after the node is updated.

### --installdir

The full path to the parent of the base installation directory of the Eclipse GlassFish software on the host, for example, `/export/glassfish7`.

### --nodedir

The path to the directory that is to contain Eclipse GlassFish instances that are created on the node. If a relative path is specified, the path is relative to the `as-install` directory, where `as-install` is the base installation directory of the Eclipse GlassFish software on the host.

### --sshport

The port to use for SSH connections to this node's host. The default depends on whether this subcommand is run to enable SSH communication for the node:

- If the node is already enabled for communication over SSH, the default is to leave the port unchanged.
- If this subcommand is run to enable SSH communication for the node, the default port is 22.

If the `--nodehost` is set to `localhost`, the `--sshport` option is ignored.

### --sshuser

The user on this node's host that is to run the process for connecting to the host through SSH. The default depends on whether this subcommand is run to enable SSH communication for the node:

- If the node is already enabled for communication over SSH, the default is to leave the user unchanged.
- If this subcommand is run to enable SSH communication for the node, the default is the user that is running the DAS process.

If the `--nodehost` option is set to `localhost`, the `--sshuser` option is ignored.

### --sshkeyfile

The absolute path to the SSH private key file for user that the `--sshuser` option specifies. This file is used for authentication to the `sshd` daemon on the node's host.



Eclipse GlassFish also supports password authentication through the `AS_ADMIN_SSHPASSWORD` entry in the password file. The password file is specified in the `--passwordfile` option of the `asadmin(1M)` utility.

If the SSH private key file is protected by a passphrase, the password file must contain the `AS_ADMIN_SSHKEYPASSPHRASE` entry.

The path to the key file must be reachable by the DAS and the key file must be readable by the DAS. The default depends on whether this subcommand is run to enable SSH communication for the node:

- If the node is already enabled for communication over SSH, the default is to leave the key file unchanged.
- If this subcommand is run to enable SSH communication for the node, the default is the key file in the user's `.ssh` directory. If multiple key files are found, the subcommand uses the following order of preference:
  1. `id_rsa`
  2. `id_dsa`
  3. `identity`

#### `--force`

Specifies whether the node is updated even if validation of the node's parameters fails. To validate a node's parameters, the DAS must be able to contact the node's host through SSH. Possible values are as follows:

##### `false`

The node is not updated if validation of the node's parameters fails (default).

##### `true`

The node is updated even if validation of the node's parameters fails.

## Operands

### `node-name`

The name of the node to update. The node must exist. Otherwise, an error occurs.

## Examples

### Example 1 Updating the Host That a Node Represents

This example updates the host that the node `lssh` represents to `sj04`.

```
asadmin> update-node-ssh --nodehost sj04 lssh  
Command update-node-ssh executed successfully.
```

## Example 2 Forcing the Update of a Node

This example forces the update of the node `sj01` to enable the node to communicate over SSH.

```
asadmin> update-node-ssh --force sj01  
Warning: some parameters appear to be invalid.  
Could not connect to host sj01 using SSH.  
Could not authenticate. Tried authenticating with specified key at  
/home/gfuser/.ssh/id_rsa  
Continuing with node update due to use of --force.  
Command update-node-ssh executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-dcom\(1\)](#), [create-node-config\(1\)](#), [create-node-ssh\(1\)](#), [delete-node-config\(1\)](#), [delete-node-dcom\(1\)](#), [delete-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-nodes\(1\)](#), [uninstall-node\(1\)](#), [uninstall-node-dcom\(1\)](#), [uninstall-node-ssh\(1\)](#), [update-node-config\(1\)](#), [update-node-dcom\(1\)](#)

# update-password-alias

Updates a password alias

## Synopsis

```
asadmin [asadmin-options] update-password-alias [--help]
aliasname
```

## Description

This subcommand updates the password alias IDs in the named target. An alias is a token of the form `#{ALIAS=password-alias-password}`. The password corresponding to the alias name is stored in an encrypted form. The `update-password-alias` subcommand takes both a secure interactive form (in which the user is prompted for all information) and a more script-friendly form, in which the password is propagated on the command line.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

`--help`

`-?`

Displays the help text for the subcommand.

## Operands

### aliasname

This is the name of the password as it appears in `domain.xml`.

## Examples

### Example 1 Updating a Password Alias

```
asadmin> update-password-alias jmspassword-alias  
Please enter the alias password>  
Please enter the alias password again>  
Command update-password-alias executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-password-alias\(1\)](#), [delete-password-alias\(1\)](#), [list-password-aliases\(1\)](#)

# uptime

Returns the length of time that the DAS has been running

## Synopsis

```
asadmin [asadmin-options] uptime [--help]
```

## Description

The **uptime** subcommand returns the length of time that the domain administration server (DAS) has been running since it was last restarted.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help**

**-?**

Displays the help text for the subcommand.

## Examples

### Example 1 Showing How Long the DAS Has Been Running

This example shows the length of time that the DAS has been running.

```
asadmin> uptime
Uptime: 2 days, 1 hours, 30 minutes, 18 seconds, Total milliseconds: 178218706
Command uptime executed successfully.
```

## Exit Status

**0**

subcommand executed successfully

1

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-domains\(1\)](#), [start-domain\(1\)](#), [stop-domain\(1\)](#)

# validate-dcom

Tests the connection over DCOM to a remote host

## Synopsis

```
asadmin [asadmin-options] validate-dcom [--help]
[--windowsuser windows-user] [--windowsdomain windows-domain]
[--remotetestdir remote-test-directory]
[--verbose={false|true}] host-name
```

## Description

The **validate-dcom** subcommand tests the connection over the Distributed Component Object Model (DCOM) remote protocol to the remote host that is specified as the operand of the subcommand. The DCOM protocol is available only on Windows systems.

The prerequisites for running this subcommand are as follows:

- DCOM must be configured on the host where the domain administration server (DAS) is running and on the remote host that is specified as the operand of the subcommand.
- The following ports must be open on the remote host:
  - DCOM port 135 or 139
  - Windows Shares port 445
- The Server Windows Service is enabled on the remote host.

This subcommand verifies whether the prerequisites for creating a DCOM node or creating a Eclipse GlassFish instance on a DCOM node are met. If this subcommand fails, any attempt to create a DCOM node or create an instance on a DCOM node will also fail.

You may run this command from any machine that can contact the DAS.

The subcommand tests the connection over DCOM to the remote host by performing the following operations on the remote host:

- Resolving the host name
- Connecting to DCOM through port 135 or 139
- Connecting to Windows Shares through port 445
- Copying a script that is named **delete\_me.bat** in the folder that is specified by the **--remotetestdir** option

- Running the script to obtain a listing of the folder in which the `delete_me.bat` was written

By default, the subcommand displays no information about the operations that are performed to test the connection to the remote host. To display information about these operations, set the `--verbose` option to `true`.

This subcommand is supported in remote mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### `--help`

`-?`

Displays the help text for the subcommand.

#### `--windowsuser`

`-w`

The user on the remote host that is to run the process for connecting to that host through DCOM. The default is the user that is running the DAS process.

#### `--windowsdomain`

`-d`

The name of the Windows domain that contains the user that the `--windowsuser` option specifies. The default is the name of the host on which the subcommand is run.

#### `--remotetestdir`

Specifies the folder on the remote host in which the subcommand creates the `delete_me.bat` file. The user that the `--windowsuser` option specifies must have write access to this folder. Otherwise an error occurs. The default is `C:\`

#### `--verbose`

`-v`

Specifies whether the subcommand displays information about the operations that are performed to test the connection to the remote host.

Possible values are as follows:

##### `false`

No information about the operations that are performed to test the connection is displayed (default).

##### `true`

The subcommand displays information about the operations that are performed to test the

connection.

If the `--verbose` option is true and the `AS_DEBUG` environment variable is set, the subcommand also displays the command line for each process that is running on the remote host.

## Operands

### host-name

The name of the host to which to test the connection over DCOM.

## Examples

### Example 1 Testing the Connection Over DCOM to a Remote Host

This example tests the connection over DCOM to the host `wpmd12`.

```
asadmin> validate-dcom --wpmd12
Command validate-dcom executed successfully.
```

### Example 2 Verbosely Testing the Connection Over DCOM to a Remote Host

This example tests the connection over DCOM to the host `wpmd12` and displays information about the operations that are performed to test the connection to the remote host.

```
asadmin> validate-dcom --verbose wpmndl2

Successfully resolved host name to: wpmndl2/192.168.122.106
Successfully connected to DCOM Port at port 135 on host wpmndl2.
Successfully connected to NetBIOS Session Service at port 139 on host wpmndl2.
Successfully connected to Windows Shares at port 445 on host wpmndl2.
Successfully accessed C: on wpmndl2 using DCOM.
Successfully wrote delete_me.bat to C: on wpmndl2 using DCOM.
Successfully accessed WMI (Windows Management Interface) on wpmndl2. There are 40
processes running on wpmndl2.
Successfully ran the test script on wpmndl2 using DCOM.
The script simply ran the DIR command. Here are the first few lines from the
output of the dir command on the remote machine:

C:\Windows\system32>dir C:\
Volume in drive C has no label.
Volume Serial Number is XXXX-XXX

Directory of C:\

12/05/2011  10:21 AM           63 .asadminpass
02/15/2011  01:08 PM      <DIR>       aroot
12/05/2011  04:43 PM           8 delete_me.bat
03/03/2011  10:36 AM      <DIR>       export

Command validate-dcom executed successfully.
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[create-node-dcom\(1\)](#), [delete-node-dcom\(1\)](#), [list-nodes\(1\)](#), [ping-node-dcom\(1\)](#), [update-node-dcom\(1\)](#)

# validate-multicast

Validates that multicast transport is available for clusters

## Synopsis

```
asadmin [asadmin-options] validate-multicast [--help]
[--multicastport multicastport]
[--multicastaddress multicastaddress]
[--bindaddress bindaddress]
[--sendperiod sendperiod]
[--timeout timeout]
[--timetolive timetolive]
[--verbose={false|true}]
```

## Description

The **validate-multicast** subcommand validates that multicast transport is available for clusters. You should run this subcommand at the same time on each of the hosts to be validated. This subcommand is available in local mode.

 Do not run the **validate-multicast** subcommand using the DAS and cluster's multicast address and port values while the DAS and cluster are running. Doing so results in an error.

The **validate-multicast** subcommand must be run at the same time on two or more machines to validate whether multicast messages are being received between the machines.

As long as all machines see each other, multicast is validated to be working properly across the machines. If the machines are not seeing each other, set the **--bindaddress** option explicitly to ensure that all machines are using interface on same subnet, or increase the **--timetolive** option from the default of 4. If these changes fail to resolve the multicast issues, ask the network administrator to verify that the network is configured so the multicast messages can be seen between all the machines used to run the cluster.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

**--help****-?**

Displays the help text for the subcommand.

**--multicastport**

The port for the multicast socket on which the Group Management Service (GMS) listens for group events. Specify a standard UDP port number in the range 2048-49151. The default is **2048**.

**--multicastaddress**

The address for the multicast socket on which the GMS listens for group events. Specify a class D IP address. Class D IP addresses are in the range **224.0.0.0** to **239.255.255.255**, inclusive. The address **224.0.0.0** is reserved and should not be used. The default is **228.9.3.1**.

**--bindaddress**

The local interface to receive multicast datagram packets for the GMS. The default is to use all available binding interfaces.

On a multi-home machine (possessing two or more network interfaces), this attribute enables you to indicate which network interface is used for the GMS. This value must be a local network interface IP address.

**--sendperiod**

The number of milliseconds between test messages sent between nodes. The default is **2000**.

**--timeout**

The number of seconds before the subcommand times out and exits. The default is **20**. You can also exit this subcommand using Ctrl-C.

**--timetolive**

The default time-to-live for multicast packets sent out on the multicast socket in order to control the scope of the multicasts. The time-to-live value must be between zero and 255 inclusive. The default is the JDK default or a minimum defined by a constant in the GMS subsystem, whichever is lower. To see the time-to-live value being used, use the **--verbose** option.

**--verbose**

If used without a value or set to **true**, provides additional debugging information. The default is **false**.

## Examples

### Example 1 Validating multicast transport

Run from host **machine1**:

```
asadmin> validate-multicast
Will use port 2,048
Will use address 228.9.3.1
Will use bind address null
Will use wait period 2,000 (in milliseconds)

Listening for data...
Sending message with content "machine1" every 2,000 milliseconds
Received data from machine1 (loopback)
Received data from machine2
Exiting after 20 seconds. To change this timeout, use the --timeout command line option.
Command validate-multicast executed successfully
```

Run from host **machine2**:

```
asadmin> validate-multicast
Will use port 2,048
Will use address 228.9.3.1
Will use bind address null
Will use wait period 2,000 (in milliseconds)

Listening for data...
Sending message with content "machine2" every 2,000 milliseconds
Received data from machine2 (loopback)
Received data from machine1
Exiting after 20 seconds. To change this timeout, use the --timeout command line option.
Command validate-multicast executed successfully
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

[get-health\(1\)](#)

# verify-domain-xml

Verifies the content of the domain.xml file

## Synopsis

```
asadmin [asadmin-options] verify-domain-xml [--help]
[--domaindir domain-dir] [domain-name]
```

## Description

Verifies the content of the `domain.xml` file by checking the following:

- That the `domain.xml` file can be parsed
- That the names for elements that have them are unique

This subcommand is supported in local mode only.

## Options

### asadmin-options

Options for the `asadmin` utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### `-h --help`

Displays the help text for the subcommand.

#### `--domaindir`

Specifies the domain root directory, where the domains are located. The path must be accessible in the file system. The default is `as-install/domains`.

## Operands

### `domain_name`

Specifies the name of the domain. The default is `domain1`.

## Examples

## Example 1 Using verify-domain-xml

```
asadmin> verify-domain-xml  
All Tests Passed.  
domain.xml is valid
```

## Exit Status

**0**

command executed successfully

**1**

error in executing the command

## See Also

[asadmin\(1M\)](#)

# version

Displays version information for Eclipse GlassFish

## Synopsis

```
asadmin [asadmin-options] version [--help]
[--verbose={false|true}]
[--local={false|true}]
```

## Description

The **version** subcommand displays version information for Eclipse GlassFish. By default, if the subcommand cannot contact the domain administration server (DAS), the subcommand retrieves the version information locally and displays a warning message.

This subcommand is supported in remote mode and local mode.

## Options

### asadmin-options

Options for the **asadmin** utility. For information about these options, see the [asadmin\(1M\)](#) help page.

#### --help

#### -?

Displays the help text for the subcommand.

#### --verbose

#### -v

If this option is set to **true**, the subcommand provides the version of the Java Runtime Environment (JRE) that the server is running. The default is **false**.

#### --local

If this option is set to **true**, the subcommand obtains the version locally from the installation of Eclipse GlassFish on the host where the subcommand is run.

If this option is set to **false** (default), the subcommand attempts to contact the DAS to obtain the version. If the attempt to contact the DAS fails, the subcommand retrieves the version locally and displays a warning message.

# Examples

## Example 1 Obtaining Version Information From a Running DAS

```
asadmin> version
Version = Eclipse GlassFish 7.0.0 (build 34)
Command version executed successfully.
```

## Example 2 Obtaining Version Information When the DAS Cannot be Reached

```
asadmin> version
Version string could not be obtained from Server [localhost:4848] for some reason.
(Turn debugging on e.g. by setting AS_DEBUG=true in your environment, to see the
details).
Using locally retrieved version string from version class.
Version = Eclipse GlassFish 7.0.0 (build 34)
Command version executed successfully.
```

## Example 3 Obtaining Version Information Locally

```
asadmin> version --local
Using locally retrieved version string from version class.
Version = Eclipse GlassFish 7.0.0 (build 34)
Command version executed successfully.
```

# Exit Status

**0**

subcommand executed successfully

**1**

error in executing the subcommand

## See Also

[asadmin\(1M\)](#)

[list-modules\(1\)](#)

# 2 Eclipse GlassFish 7 Utility Commands

This section describes Eclipse GlassFish utility commands.

# appclient

Launches the Application Client Container and invokes the client application typically packaged in the application JAR file

## Synopsis

```
appclient [client_application_classfile | -client client_application_jar]
[-mainclass main_class_name | -name display_name]
[-xml sun-acc.xml file] [-textauth]
[-targetserver host[:port][,host[:port]...]]
[-user username] [-passwordfile password_file]
[application-options]

appclient [jvm-options]
[-mainclass main_class_name | -name display_name]
[-xml client_config_xml_file] [-textauth]
[-targetserver host[:port][,host[:port]...]]
[-user username] [-passwordfile password_file]
class-selector [application-options]
```

## Description

Use the `appclient` command to launch the Application Client Container and invoke a client application that is typically packaged in an application JAR file. The application client JAR file is specified and created during deployment by the Administration Console or the `asadmin deploy` command with the `--retrieve` option. You can also retrieve the client JAR file using the `asadmin get-client-stubs` command.

The Application Client Container is a set of Java classes, libraries, and other files that are required to execute a first-tier application client program on a Virtual Machine for the Java platform (JVM machine). The Application Client Container communicates with the server using RMI-IIOP.

The client JAR file that is retrieved after deploying an application should be passed with the `-client` or `-jar` option when running the `appclient` utility. The client JAR file name is of the form app-name`Client.jar`. For multiple application clients in an EAR file, you must use the `-mainclass` or `-name` option to specify which client to invoke.

If the application client is a stand-alone module or the only client in an EAR file, the Application Client Container can find the client without using the `-mainclass` or `-name` options. If you provide a `-mainclass` or `-name` value that does not match what is in the client, the Application Client Container launches the client anyway but issues a warning that the selection did not match the information in the client. The warning also displays what the actual main class and name values are for the client.

# Options

## jvm-options

optional; you can set JVM options for the client application. These can be any valid `java` command options except `-client` or `-jar`. JVM options can be intermixed with other `appclient` command options as long as both types of options appear before the class-selector.

## client\_application\_classfile

optional; the file system pathname of the client application `.class` file. A relative pathname must be relative to the current directory. This class file must contain the `main()` method to be invoked by the Application Client Container.

If you use `client_application_classfile` and the class is dependent on other user classes, you must also set the classpath. You can either use the `-classpath` JVM option in the `appclient` command or set the `CLASSPATH` environment variable. For more information about setting a classpath, see Setting the Class Path, Oracle Solaris Version (<http://docs.oracle.com/javase/6/docs/technotes/tools/solaris/classpath.html>) or Setting the Class Path, Windows Version (<http://docs.oracle.com/javase/6/docs/technotes/tools/windows/classpath.html>).

## -client

optional; the name and location for the client JAR file.

## -mainclass

optional; the full classname of the main client application as specified in the `Main-Class` entry in the `MANIFEST.MF` file. Used for a multiple client applications. By default, uses the class specified in the `client jar`. For example, `com.example.test.AppClient`.

## -name

optional; the display name for the client application. Used for multiple client applications. By default, the display name is specified in the client jar `application-client.xml` file which is identified by the `display-name` attribute.

## -xml

optional if using the default domain, instance, and name (`sun-acc.xml`), otherwise it is required; identifies the name and location of the client configuration XML file. If not specified, defaults to the `sun-acc.xml` file in the domain-dir/`config` directory.

## -textauth

optional; used to specify using text format authentication when authentication is needed.

## -targetserver

optional; a comma-separated list of one or more server specifications for ORB endpoints. Each server specification must include at least the host. Optionally, a server specification can include the port as well. If the port is omitted from a server specification, the default value, `3700`, is used for that host.

**-user**

optional; the application user who is authorized to have access to particular guarded components in the application, such as EJB components.

**-passwordfile**

optional; specifies the name, including the full path, of a file that contains the password for application clients in the following format:

```
PASSWORD=appclient-password
```

If this option is omitted, the password is specified interactively at the command prompt.



Avoid specifying a password interactively at the command prompt. Such a password can be seen by users who can run commands to display running processes and the commands to start them, such as `ps`.

For security reasons, a password that is specified as an environment variable is not read by the `appclient` utility.

**class-selector**

required; you must specify the client application class using one of the following class selectors.

**-jar jar-file**

the name and location of the client JAR file. The application client JAR file is specified and created during deployment by the `asadmin deploy` command. If specified, the `-classpath` setting is ignored in deference to the `Class-Path` setting in the client JAR file's manifest.

**class-name**

the fully qualified name of the application client's main class. The Application Client Container invokes the `main` method of this class to start the client. For example, `com.example.test.AppClient`. If you use `class-name` as the class selector, you must also set the classpath. You can either use the `-classpath` JVM option in the `appclient` command or set the `CLASSPATH` environment variable. For more information about setting a classpath, see Setting the Class Path, Oracle Solaris Version (<http://docs.oracle.com/javase/6/docs/technotes/tools/solaris/classpath.html>) or Setting the Class Path, Windows Version (<http://docs.oracle.com/javase/6/docs/technotes/tools/windows/classpath.html>).

**application-options**

optional; you can set client application arguments.

# Examples

## Example 1 Using the `appclient` command

```
appclient -xml sun-acc.xml -jar myclientapp.jar scott sample
```

Where: `sun-acc.xml` is the name of the client configuration XML file, `myclientapp.jar` is the client application `.jar` file, and `scott` and `sample` are arguments to pass to the application. If `sun-acc.xml` and `myclientapp.jar` are not in the current directory, you must give the absolute path locations; otherwise the relative paths are used. The relative path is relative to the directory where the command is being executed.

## Attributes

See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Unstable

## See Also

[asadmin\(1M\)](#)

[get-client-stubs\(1\)](#), [package-appclient\(1M\)](#)

The script content on this page is for navigation purposes only and does not alter the content in any way.

# asadmin

Utility for performing administrative tasks for Eclipse GlassFish

## Synopsis

```
asadmin [--host host]
[--port port]
[--user admin-user]
[--passwordfile filename]
[--terse={true|false}]
[--secure={false|true}]
[--echo={true|false}]
[--interactive={true|false}]
[--detach={true|false}]
[--help]
[subcommand [options] [operands]]
```

## Description

Use the `asadmin` utility to perform administrative tasks for Eclipse GlassFish. You can use this utility instead of the Administration Console interface.

## Subcommands of the asadmin Utility

The subcommand identifies the operation or task that you are performing. Subcommands are case-sensitive. Each subcommand is either a local subcommand or a remote subcommand.

- A local subcommand can be run without a running domain administration server (DAS). However, to run the subcommand and have access to the installation directory and the domain directory, the user must be logged in to the machine that hosts the domain.
- A remote subcommand is always run by connecting to a DAS and running the subcommand there. A running DAS is required.

## asadmin Utility Options and Subcommand Options

Options control the behavior of the `asadmin` utility and its subcommands. Options are also case-sensitive.

The `asadmin` utility has the following types of options:

- `asadmin` utility options. These options control the behavior of the `asadmin` utility, not the

subcommand. The `asadmin` utility options may precede or follow the subcommand, but `asadmin` utility options after the subcommand are deprecated. All `asadmin` utility options must either precede or follow the subcommand. If `asadmin` utility options are specified both before and after the subcommand, an error occurs. For a description of the `asadmin` utility options, see the "Options" section of this help information.

- Subcommand options. These options control the behavior of the subcommand, not the `asadmin` utility. Subcommand options must follow the subcommand. For a description of a subcommand's options, see the help information for the subcommand.

A subcommand option may have the same name as an `asadmin` utility option, but the effects of the two options are different.

The `asadmin` utility options and some subcommand options have a long form and a short form.

- The long form of an option has two dashes (`--`) followed by an option word.
- The short form of an option has a single dash (`-`) followed by a single character.

For example, the long form and the short form of the option for specifying terse output are as follows:

- Long form: `--terse`
- Short form: `-t`

Most options require argument values, except Boolean options, which toggle to enable or disable a feature.

## Operands of asadmin Subcommands

Operands specify the items on which the subcommand is to act. Operands must follow the argument values of subcommand options, and are set off by a space, a tab, or double dashes (`--`). The `asadmin` utility treats anything that follows the subcommand options and their values as an operand.

### Escape Characters in Options for the asadmin Utility

Escape characters are required in options of the `asadmin` utility for the following types of characters:

- Meta characters in the UNIX operating system. These characters have special meaning in a shell. Meta characters in the UNIX operating system include: `\, . !$%^&*|{}[]"'"``.

To disable these characters, use the backslash (`\`) escape character or enclose the entire command-line argument in single quote (`'`) characters.

The following examples illustrate the effect of escape characters on the `*` character. In these examples, the current working directory is the domains directory.

- The following command, without the escape character, echoes all files in the current directory:

```
prompt% echo *
domain1 domain2
```

- The following command, in which the backslash (\) escape character precedes the **character**, **echoes the** character:

```
prompt% echo \*
*
```

- The following command, in which the **character is enclosed in single quote (')** characters, **echoes the** character:

```
prompt% echo '*'
*
```

The escape character is also a special character in the UNIX operating system and in the Java language. Therefore, in the UNIX operating system and in multimode, you must apply an additional escape character to every escape character in the command line. This requirement does not apply to the Windows operating system.

For example, the backslash (\) UNIX operating system meta character in the option argument **Test\Escape\Character** is specified on UNIX and Windows systems as follows:

- On UNIX systems, each backslash must be escaped with a second backslash:

```
Test\\Escape\\Character
```

- On Windows systems, no escape character is required:

```
Test\Escape\Character
```



In contexts where meta characters in the UNIX operating system are unambiguous, these characters do not require escape characters. For example, in the **set(1)** subcommand, the value that is to be set is specified as **name`=value**. Because **name** can never include an equals sign, no escape character is required to disable the equals sign. Therefore, everything after the equals sign is an uninterpreted string that the **'set** subcommand uses unchanged.

- Spaces. The space is the separator in the command-line interface. To distinguish a space in a command-line argument from the separator in the command-line interface, the space must be escaped as follows:

- For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, use the backslash (\) escape character or enclose the entire command-line argument in single quote ('') characters or double quote ("") characters.
- For the Windows operating system in single mode, enclose the entire command-line argument in double quote ("") characters.
- Option delimiters. The **asadmin** utility uses the colon character (:) as a delimiter for some options. The backslash (\) escape character is required if the colon is part of any of the following items:
  - A property
  - An option of the Virtual Machine for the Java platform (Java Virtual Machine or JVM machine)<sup>Foot 1</sup>

For example, the operand of the subcommand **create-jvm-options(1)** specifies JVM machine options in the following format:

```
(jvm-option-name[=jvm-option-value])
[:jvm-option-name[=jvm-option-value]]*
```

Multiple JVM machine options in the operand of the **create-jvm-options** subcommand are separated by the colon (:) delimiter. If jvm-option-name or jvm-option-value contains a colon, the backslash (\) escape character is required before the colon.

The backslash (\) escape character is also required before a single quote ('') character or a double quote ("") character in an option that uses the colon as a delimiter.

When used without single quote ('') characters, the escape character disables the option delimiter in the command-line interface.

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, the colon character and the backslash character in an option that uses the colon as a delimiter must be specified as follows:

- To pass a literal backslash to a subcommand, two backslashes are required. Therefore, the colon (:) must be escaped by two backslashes (\\\).
- To prevent a subcommand from treating the backslash as a special character, the backslash must be escaped. As a result, two literal backslashes (\\\) must be passed to the subcommand. To prevent the shell from interpreting these backslashes as special characters, each backslash must be escaped. Therefore, the backslash must be specified by a total of four backslashes ( \\\\\\).

For the Windows operating system in single mode, a backslash (\) is required to escape the colon (:) and the backslash (\) in an option that uses the colon as a delimiter.

Instead of using the backslash (\) escape character, you can use the double quote ("") character or single

quote (') character. The effects of the different types of quote characters on the backslash (\) character are as follows:

- Between double quote ("") characters, the backslash (\) character is a special character.
- Between single quote (') characters, the backslash (\) character is not a special character.

## Requirements for Using the --secure Option

The requirements for using the `--secure` option are as follows:

- The domain that you are administering must be configured for security.
- The `security-enabled` attribute of the `http-listener` element in the DAS configuration must be set to `true`.

To set this attribute, use the `set` subcommand.

## Server Restart After Creation or Deletion

When you use the `asadmin` subcommands to create or delete a configuration item, you must restart the DAS for the change to take effect. To restart the DAS, use the `restart-domain(1)` subcommand.

## Help Information for Subcommands and the asadmin Utility

To obtain help information for an `asadmin` utility subcommand, specify the subcommand of interest as the operand of the `help` subcommand. For example, to obtain help information for the `start-domain(1)` subcommand, type:

```
asadmin help start-domain
```

If you run the `help` subcommand without an operand, this help information for the `asadmin` utility is displayed.

To obtain a listing of available `asadmin` subcommands, use the `list-commands(1)` subcommand.

## Options

**--host**

**-H**

The machine name where the DAS is running. The default value is `localhost`.

**--port**

**-P**

The HTTP port or HTTPS port for administration. This port is the port in the URL that you specify in your web browser to manage the domain. For example, in the URL `http://localhost:4949`, the port

is 4949.

The default port number for administration is 4848.

#### --user

##### -u

The user name of the authorized administrative user of the DAS.

If you have authenticated to a domain by using the [asadmin login](#) command, you need not specify the --user option for subsequent operations on the domain.

#### --passwordfile

##### -W

Specifies the name, including the full path, of a file that contains password entries in a specific format.

Note that any password file created to pass as an argument by using the --passwordfile option should be protected with file system permissions. Additionally, any password file being used for a transient purpose, such as setting up SSH among nodes, should be deleted after it has served its purpose.

The entry for a password must have the AS\_ADMIN\_ prefix followed by the password name in uppercase letters, an equals sign, and the password.

The entries in the file that are read by the [asadmin](#) utility are as follows:

- AS\_ADMIN\_PASSWORD=administration-password
- AS\_ADMIN\_MASTERPASSWORD=master-password

The entries in this file that are read by subcommands are as follows:

- AS\_ADMIN\_NEWPASSWORD=new-administration-password (read by the [start-domain\(1\)](#) subcommand)
- AS\_ADMIN\_USERPASSWORD=user-password (read by the [create-file-user\(1\)](#) subcommand)
- AS\_ADMIN\_ALIASPASSWORD=alias-password (read by the [create-password-alias\(1\)](#) subcommand)
- AS\_ADMIN\_MAPPEDPASSWORD=mapped-password (read by the [create-connector-security-map\(1\)](#) subcommand)
- AS\_ADMIN\_WINDOWSPASSWORD=windows-password (read by the [create-node-dcom\(1\)](#), [install-node-dcom\(1\)](#), and [update-node-dcom\(1\)](#) subcommands)
- AS\_ADMIN\_SSHPASSWORD=sshd-password (read by the [create-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-ssh\(1\)](#), and [update-node-ssh\(1\)](#) subcommands)
- AS\_ADMIN\_SSHKEYPASSPHRASE=sshd-passphrase (read by the [create-node-ssh\(1\)](#), [install-node\(1\)](#), [install-node-ssh\(1\)](#), and [update-node-ssh\(1\)](#) subcommands)
- AS\_ADMIN\_JMSDBPASSWORD= jdbc-user-password (read by the [configure-jms-cluster\(1\)](#) subcommand)

These password entries are stored in clear text in the password file. To provide additional security, the [create-password-alias](#) subcommand can be used to create aliases for passwords that are used by

remote subcommands. The password for which the alias is created is stored in an encrypted form. If an alias exists for a password, the alias is specified in the entry for the password as follows:

```
AS_ADMIN_password-name=${ALIAS=password-alias-name}
```

For example:

```
AS_ADMIN_SSHPASSWORD=${ALIAS=ssh-password-alias}
AS_ADMIN_SSHKEYPASSPHRASE=${ALIAS=ssh-key-passphrase-alias}
```

In domains that do not allow unauthenticated login, all remote subcommands must specify the administration password to authenticate to the DAS. The password can be specified by one of the following means:

- Through the `--passwordfile` option
- Through the `login(1)` subcommand
- Interactively at the command prompt

The `login` subcommand can be used to specify only the administration password. For other passwords that remote subcommands require, use the `--passwordfile` option or specify them at the command prompt.

After authenticating to a domain by using the `asadmin login` command, you need not specify the administration password through the `--passwordfile` option for subsequent operations on the domain. However, only the `AS_ADMIN_PASSWORD` option is not required. You still must provide the other passwords, for example, `AS_ADMIN_USERPASSWORD`, when required by individual subcommands, such as `update-file-user(1)`.

For security reasons, a password that is specified as an environment variable is not read by the `asadmin` utility.

The master password is not propagated on the command line or an environment variable, but can be specified in the file that the `--passwordfile` option specifies.

The default value for `AS_ADMIN_MASTERPASSWORD` is `changeit`.

#### `--terse`

#### `-t`

If true, output data is very concise and in a format that is optimized for use in scripts instead of for reading by humans. Typically, descriptive text and detailed status messages are also omitted from the output data. Default is false.

#### `--secure`

#### `-s`

If set to true, uses SSL/TLS to communicate with the DAS.

The default is false.

**--echo****-e**

If set to true, the command-line statement is echoed on the standard output. Default is false.

**--interactive****-I**

If set to true, only the required options are prompted.

The default depends on how the `asadmin` utility is run:

- If the `asadmin` utility is run from a console window, the default is `true`.
- If the `asadmin` utility is run without a console window, for example, from within a script, the default is `false`.

**--detach**

If set to `true`, the specified `asadmin` subcommand is detached and executed in the background in detach mode. The default value is `false`.

The `--detach` option is useful for long-running subcommands and enables you to execute several independent subcommands from one console or script.

The `--detach` option is specified before the subcommand. For example, in single mode, `asadmin --detach` subcommand.

Job IDs are assigned to subcommands that are started using `asadmin --detach`. You can use the `list-jobs(1)` subcommand to view the jobs and their job IDs, the `attach(1)` subcommand to reattach to the job and view its status and output, and the `configure-managed-jobs(1)` subcommand to configure how long information about the jobs is kept.

**--help****-?**

Displays the help text for the `asadmin` utility.

## Examples

### Example 1 Running an `asadmin` Utility Subcommand in Single Mode

This example runs the `list-applications(1)` subcommand in single mode. In this example, the default values for all options are used.

The example shows that the application `hello` is deployed on the local host.

```
asadmin list-applications  
hello <web>
```

Command list-applications executed successfully.

## Example 2 Specifying an `asadmin` Utility Option With a Subcommand

This example specifies the `--host asadmin` utility option with the `list-applications` subcommand in single mode. In this example, the DAS is running on the host `srvr1.example.com`.

The example shows that the applications `basic-ezcomp`, `scrumtoys`, `ejb31-war`, and `automatic-timer-ejb` are deployed on the host `srvr1.example.com`.

```
asadmin --host srvr1.example.com list-applications  
basic-ezcomp <web>  
scrumtoys <web>  
ejb31-war <ejb, web>  
automatic-timer-ejb <ejb>
```

Command list-applications executed successfully.

## Example 3 Specifying an `asadmin` Utility Option and a Subcommand Option

This example specifies the `--host asadmin` utility option and the `--type` subcommand option with the `list-applications` subcommand in single mode. In this example, the DAS is running on the host `srvr1.example.com` and applications of type `web` are to be listed.

```
asadmin --host srvr1.example.com list-applications --type web  
basic-ezcomp <web>  
scrumtoys <web>  
ejb31-war <ejb, web>
```

Command list-applications executed successfully.

## Example 4 Escaping a Command-Line Argument With Single Quote Characters

The commands in this example specify the backslash (\) UNIX operating system meta character and the colon (:) option delimiter in the property value `c:\extras\pmdapp`.

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, the backslash (\) is required to escape the backslash (\) meta character and the colon (:) option delimiter:

```
asadmin deploy --property extras.home='c:\\\\extras\\\\pmdapp' pmdapp.war
Application deployed with name pmdapp.
Command deploy executed successfully
```

For the Windows operating system in single mode, the single quote ('') characters eliminate the need for other escape characters:

```
asadmin deploy --property extras.home='c:\\extras\\pmdapp' pmdapp.war
Application deployed with name pmdapp.
Command deploy executed successfully
```

## Example 5 Specifying a UNIX Operating System Meta Character in an Option

The commands in this example specify the backslash (\) UNIX operating system meta character in the option argument `Test\\Escape\\Character`.

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, the backslash (\) is required to escape the backslash (\) meta character:

```
asadmin --user admin --passwordfile gfpass create-jdbc-connection-pool
--datasourceclassname sampleClassName
--description Test\\\\Escape\\\\Character
sampleJDBCConnectionPool
```

For the Windows operating system in single mode, no escape character is required:

```
asadmin --user admin --passwordfile gfpass create-jdbc-connection-pool
--datasourceclassname sampleClassName
--description Test\\Escape\\Character
sampleJDBCConnectionPool
```

## Example 6 Specifying a Command-Line Argument That Contains a Space

The commands in this example specify spaces in the operand `C:\Documents and Settings\gfuser\apps\hello.war`.

For all operating systems in single mode or multimode, the entire operand can be enclosed in double quote ("") characters:

```
asadmin deploy "C:\Documents and Settings\gfuser\apps\hello.war"  
Application deployed with name hello.  
Command deploy executed successfully.
```

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, the entire command-line argument can be enclosed in single quote ('') characters:

```
asadmin> deploy 'C:\Documents and Settings\gfuser\apps\hello.war'  
Application deployed with name hello.  
Command deploy executed successfully.
```

Alternatively, for the UNIX operating system in single mode and multimode, and for all operating systems in multimode, the backslash (\) escape character can be used before each space in the operand. In this situation, the backslash (\) escape character is required before each backslash in the operand:

```
asadmin> deploy C:\\\\Documents\\\\ and\\\\ Settings\\\\\\gfuser\\\\\\apps\\\\\\hello.war  
Application deployed with name hello.  
Command deploy executed successfully.
```

## Example 7 Specifying a Meta Character and an Option Delimiter Character in a Property

The commands in this example specify the backslash (\) UNIX operating system meta character and the colon (:) option delimiter character in the `--property` option of the `create-jdbc-connection-pool(1)` subcommand.

The name and value pairs for the `--property` option are as follows:

```
user=dbuser
passwordfile=dbpasswordfile
DatabaseName=jdbc:derby
server=http://localhost:9092
```

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, a backslash (\) is required to escape the colon (:) and the backslash (\):

```
asadmin --user admin --passwordfile gpass create-jdbc-connection-pool
--datasourceclassname com.derby.jdbc.jdbcDataSource
--property user=dbuser:passwordfile=dbpasswordfile:
DatabaseName=jdbc\\:derby:server=http\\://localhost\\:9092 javadb-pool
```

Alternatively, the entire argument to the **--property** option can be enclosed in single quote () characters:

```
asadmin --user admin --passwordfile gpass create-jdbc-connection-pool
--datasourceclassname com.derby.jdbc.jdbcDataSource
--property 'user=dbuser:passwordfile=dbpasswordfile:
DatabaseName="jdbc:derby":server="http://localhost:9092'" javadb-pool
```

For the Windows operating system in single mode, a backslash (\) is required to escape only the colon (:), but not the backslash (\):

```
asadmin --user admin --passwordfile gpass create-jdbc-connection-pool
--datasourceclassname com.derby.jdbc.jdbcDataSource
--property user-dbuser:passwordfile-dbpasswordfile:
DatabaseName=jdbc\:derby:server=http\://localhost\:9092 javadb-pool
```

For all operating systems, the need to escape the colon (:) in a value can be avoided by enclosing the value in double quote characters or single quote characters:

```
asadmin --user admin --passwordfile gpass create-jdbc-connection-pool
--datasourceclassname com.derby.jdbc.jdbcDataSource
--property user=dbuser:passwordfile=dbpasswordfile:
DatabaseName=\"jdbc:derby\":server=\"http://localhost:9092\" javadb-pool
```

## Example 8 Specifying an Option Delimiter and an Escape Character in a JVM Option

The commands in this example specify the following characters in the `-Dlocation=c:\sun\appserver` JVM machine option:

- The colon (:) option delimiter
- The backslash (\) escape character

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, these characters must be specified as follows:

- To pass a literal backslash to a subcommand, two backslashes are required. Therefore, the colon (:) must be escaped by two backslashes (\\\).
- To prevent the subcommand from treating the backslash as a special character, the backslash must be escaped. As a result, two literal backslashes (\\) must be passed to the subcommand. To prevent the shell from interpreting these backslashes as special characters, each backslash must be escaped. Therefore, the backslash must be specified by a total of four backslashes (\\\\\\).

The resulting command is as follows:

```
asadmin create-jvm-options --target test-server  
-e -Dlocation=c:\\\\\\sun\\\\appserver
```

For the Windows operating system in single mode, a backslash (\) is required to escape the colon (:) and the backslash (\):

```
asadmin create-jvm-options --target test-server  
-e -Dlocation=c:\\sun\\appserver
```

## Example 9 Specifying an Option That Contains an Escape Character

The commands in this example specify the backslash (\) character and the double quote ("") characters in the "Hello\App"\authentication option argument.

For the UNIX operating system in single mode and multimode, and for all operating systems in multimode, a backslash (\) is required to escape the double quote character (") and the backslash (\):

```
asadmin set-web-env-entry --name="Hello User" --type=java.lang.String  
--value=techscribe --description=\"Hello\\App\"\\authentication hello
```

For the Windows operating system in single mode, a backslash (\) is required to escape only the double quote ("), but not the backslash (\):

```
asadmin set-web-env-entry --name="Hello User" --type=java.lang.String
--value=techscribe --description=\\"Hello\\App\\"authentication hello
```

## Environment Variables

Environment variables modify the default values of `asadmin` utility options as shown in the following table.

Environment Variable	<code>asadmin</code> Utility Option
<code>AS_ADMIN_TERSE</code>	<code>--terse</code>
<code>AS_ADMIN_ECHO</code>	<code>--echo</code>
<code>AS_ADMIN_INTERACTIVE</code>	<code>--interactive</code>
<code>AS_ADMIN_HOST</code>	<code>--host</code>
<code>AS_ADMIN_PORT</code>	<code>--port</code>
<code>AS_ADMIN_SECURE</code>	<code>--secure</code>
<code>AS_ADMIN_USER</code>	<code>--user</code>
<code>AS_ADMIN_PASSWORDFILE</code>	<code>--passwordfile</code>
<code>AS_ADMIN_HELP</code>	<code>--help</code>

## Attributes

See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Unstable

## See Also

[attach\(1\)](#), [configure-jms-cluster\(1\)](#), [configure-managed-jobs\(1\)](#), [create-connector-security-map\(1\)](#), [create-file-user\(1\)](#), [create-jdbc-connection-pool\(1\)](#), [create-jvm-options\(1\)](#), [create-node-dcom\(1\)](#), [create-node-ssh\(1\)](#), [create-password-alias\(1\)](#), [deploy\(1\)](#), [install-node\(1\)](#), [install-node-dcom\(1\)](#), [install-node-ssh\(1\)](#), [list-applications\(1\)](#), [list-commands\(1\)](#), [list-jobs\(1\)](#), [login\(1\)](#), [restart-domain\(1\)](#), [set\(1\)](#), [set-web-env-entry\(1\)](#), [start-domain\(1\)](#), [update-file-user\(1\)](#), [update-node-dcom\(1\)](#), [update-node-ssh\(1\)](#)

[attributes\(5\)](#)

## Footnote Legend

Footnote 1: The terms "Java Virtual Machine" and "JVM" mean a Virtual Machine for the Java platform.

+

The script content on this page is for navigation purposes only and does not alter the content in any way.

# debug-asadmin

Variant of the [asadmin](#) utility for performing administrative tasks for Eclipse GlassFish. This variant is useful for debugging local admin commands the launching of Eclipse GlassFish. It suspends immediately waiting for a debug connection to port 9008.

## Synopsis

```
debug-asadmin [--host host]
[--port port]
[--user admin-user]
[--passwordfile filename]
[--terse={true|false}]
[--secure={false|true}]
[--echo={true|false}]
[--interactive={true|false}]
[--detach={true|false}]
[--help]
[subcommand [options] [operands]]
```

## Description

Use the [debug-asadmin](#) utility to debug local admin commands and the launching of the Eclipse GlassFish. See the [asadmin](#) command for full documentation.

[attributes\(5\)](#)

# capture-schema

Stores the database metadata (schema) in a file for use in mapping and execution

## Synopsis

```
capture-schema -username name -password password  
[-dburl url] [-driver jdbc_driver_classname]  
[-schemaname schemaname] [-table tablename]  
-out filename
```

## Description

Stores the database metadata (schema) in a file.

Run `capture-schema` as the same database user that owns the table(s), and use that same username with the `-username` option (and `-schemaname`, if required).

When running `capture-schema` against an Oracle database, you should grant the database user running the `capture-schema` command the `ANALYZE ANY TABLE` privilege.

## Options

### `-username`

user name for authenticating access to a database.

### `-password`

password for accessing the selected database.

### `-dburl`

JDBC URL required by the driver for accessing a database.

### `-driver`

JDBC driver classname in your `CLASSPATH`.

### `-schemaname`

name of the user schema being captured. If not specified, the default will capture metadata for all tables from all the schemas accessible to this user.

Specifying this parameter is highly recommended. Without this option, if more than one schema is accessible to this user, more than one table with the same name may be captured, which will cause problems when mapping CMP fields to tables.

The specified schema name must be uppercase.

**-table**

name of a table; multiple table names can be specified. If no table is specified, all the tables in the database or named schema are captured.

The specified table name or names are case sensitive. Be sure to match the case of the previously created table names.

**-out**

name of the output file. This option is required. If the specified output file does not contain the .dbschema suffix, it will be appended to the filename.

## Examples

### Example 1 Using the `capture-schema` command

```
capture-schema -username cantiflas -password enigma  
-dburl jdbc:oracle:thin:@sadbuttrue:1521:ora817  
-driver oracle.jdbc.driver.OracleDriver  
-schemaname CANTIFLAS -out cantiflas.dbschema
```

Where: `sun-acc.xml` is the name of the client configuration XML file, `myclientapp.jar` is the client application `.jar` file, and `scott` and `sample` are arguments to pass to the application. If `sun-acc.xml` and `myclientapp.jar` are not in the current directory, you must give the absolute path locations; otherwise the relative paths are used. The relative path is relative to the directory where the command is being executed.

## See Also

[asadmin\(1M\)](#)

# package-appclient

Packs the application client container libraries and jar files

## Synopsis

```
package-appclient
```

## Description

Use the **package-appclient** command to pack the application client container libraries and jar files into an **appclient.jar** file, which is created in the `as-install/lib` directory on the machine on which Eclipse GlassFish is installed. The **appclient.jar** file provides an application client container package targeted at remote hosts that do not contain a server installation.

After copying the **appclient.jar** file to a remote location, unjar or unzip it to get a set of libraries and jar files in the `appclient` directory under the current directory.

After unjarring on the client machine, modify `appclient/glassfish/config/asenv.conf` (`asenv.bat` for Windows) as follows:

- set `AS_WEBSERVICES_LIB` to path-to-appclient`/appclient/lib`
- set `AS_IMQ_LIB` to path-to-appclient`/appclient/mq/lib`
- set `AS_INSTALL` to path-to-appclient/**appclient**
- set `AS_JAVA` to your JDK 7 or JRE 7 home directory
- set `AS_ACC_CONFIG` to path-to-appclient/appclient/glassfish/domains/domain1/config/sun-acc.xml

Modify `appclient/glassfish/domains/domain1/config/sun-acc.xml` as follows:

- Ensure the `DOCTYPE` file references path-to-appclient/appclient/glassfish/lib/dtds
- Ensure that `target-server` address attribute references the server machine.
- Ensure that `target-server` port attribute references the ORB port on the remote machine.
- Ensure that `log-service` references a log file; if the user wants to put log messages to a log file.

To use the newly installed application client container, you must do the following:

- Obtain the application client files for your target application, including the generated `yourAppClient.jar` file.
- Execute the **appclient** utility: `appclient -client yourAppClient.jar`

# Attributes

See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Unstable

## See Also

[appclient\(1M\)](#)

# 3 Eclipse GlassFish 7 Eclipse GlassFish Concepts

This section describes concepts that are related to Eclipse GlassFish administration.

# application

Server-side Java applications and web services

## Description

The Jakarta EE platform enables applications to access systems that are outside of the application server. Applications connect to these systems through resources. The Eclipse GlassFish infrastructure supports the deployment of many types of distributed applications and is an ideal foundation for building applications based on Service Oriented Architectures (SOA). SOA is a design methodology aimed at maximizing the reuse of application services. These features enable you to run scalable and highly available Jakarta EE applications.

## See Also

[create-application-ref\(1\)](#), [deploy\(1\)](#), [list-applications\(1\)](#)

# configuration

The data set that determines how Eclipse GlassFish operates

## Description

The configuration of Eclipse GlassFish is the data set that determines how it operates. Parts of this configuration determine the operation of specific parts of Eclipse GlassFish, such as the following:

- Services, such as the transaction service
- Resources, such as databases
- Deployed applications or modules, such as web applications
- Clusters and server instances

The term configuration is also used to describe a part of the overall configuration, such as the transaction service configuration or the configuration of a database. In clustered environments, clusters or server instances can share configurations.

Examples of configuration data are port numbers, flags that enable or disable processes, application names, and so on. Most of these data points are name/value pairs, either hard-coded attributes or more flexibly defined properties.

The hierarchical structure of the configuration is explained in the dotted names page. You can view and change most of the Eclipse GlassFish configuration using either the Administration Console or the `asadmin` utility and its subcommands. To list the structure of all or part of the configuration, use the `list` subcommand. To view the value of one or more attributes or properties, use the `get` subcommand. To change the value of an attribute or property, use the `set` subcommand.

## See Also

[get\(1\)](#), [list\(1\)](#), [set\(1\)](#)

[asadmin\(1M\)](#)

[dotted-names\(5ASC\)](#)

["Configuration Tasks" in Eclipse GlassFish Administration Guide](#)

# domain

Domains have their own configurations.

## Description

A domain provides a common authentication and administration point for a collection of zero or more server instances. The administration domain encompasses several manageable resources, including instances, clusters, and their individual resources. A manageable resource, such as a server instance, may belong to only one domain.

## See Also

[asadmin\(1M\)](#)

# dotted-names

Syntax for using periods to separate name elements

## Description

A dotted name is an identifier for a particular Eclipse GlassFish element, such as a configurable or a monitorable object. A dotted name uses the period (.), known as dot, as a delimiter to separate the parts of an element name. The period in a dotted name is similar to the slash (/) character that delimits the levels in the absolute path name of a file in the UNIX file system.

The subcommands of the `asadmin` utility use dotted names as follows:

- The `list` subcommand provides the fully qualified dotted names of the management components' attributes.
- The `get` subcommand provides access to the attributes.
- The `set` subcommand enables you to modify configurable attributes and set properties.

The configuration hierarchy is loosely based on the domain's schema document, and the attributes are modifiable. The attributes of the monitoring hierarchy are read-only.

The following format is used for configuration dotted names (italic indicates replaceable):

```
config-name`.config-element-name.primary-key.attribute-name `| instance-name`.config-element-name.primary-key.`attribute-name
```

The following format is used for resource dotted names (italic indicates replaceable):

```
server-name`.resource-name.primary-key.attribute-name `| domain.resources.`resource-name.primary-key.`attribute-name
```

The following rules apply to forming dotted names:

- The top-level is configuration, server, or domain name. For example, `server-config` (default configuration), `server` (default server), or `domain1` (default domain).
- A dot (.) always separates two sequential parts of the name.
- A part of the name usually identifies a server subsystem or its specific instance. For example, `web-container`, `log-service`, `thread-pool-1`.
- If any part of the name itself contains a dot (.), then the dot must be escaped with a leading \ (backslash) so that the . (dot) does not act like a delimiter. For further information on escape characters, see the `asadmin(1M)` help page.
- An \* (asterisk) character can be used anywhere in the dotted name and acts like the wildcard character in regular expressions. Additionally, an \* can collapse all the parts of the dotted name.

For example, a long dotted name such as `this.is.really.long.hierarchy` can be abbreviated to `th*.hierarchy`. The `.` (dot) always delimits the parts of the dotted name.



Characters that have special meaning to the shell or command interpreter, such as `*` (asterisk), should be quoted or escaped as appropriate to the shell, for example, by enclosing the argument in quotes. In multimode, quotes are needed only for arguments that include spaces, quotes, or backslash.

- The `--monitor` option of the `get` and `list` subcommands selects the monitoring or configuration hierarchy. If the subcommand specifies `--monitor=false` (the default), the configuration hierarchy is selected. If the subcommand specifies `--monitor=true`, the monitoring hierarchy is selected.
- If you know the complete dotted name and do not need to use a wildcard, the `list`, `get`, and `set` subcommands treat the name differently:
  - The `list` subcommand treats a complete dotted name as the name of a parent node in the abstract hierarchy. When you specify this name to the `list` subcommand, the names of the immediate children at that level are returned. For example, the following command lists all the web modules deployed to the domain or the default server:

```
asadmin> list server.applications.web-module
```

- The `get` and `set` subcommands treat a complete dotted name as the fully qualified name of the attribute of a node (whose dotted name itself is the name that you get when you remove the last part of this dotted name). When you specify this name to the `get` or `set` subcommand, the subcommand acts on the value of that attribute, if such an attribute exists. You will never start with this case because in order to find out the names of attributes of a particular node in the hierarchy, you must use the `*` wildcard character . For example, the following dotted name returns the context root of the web application deployed to the domain or default server:

```
server.applications.web-module.JSPWiki.context-root
```

## Examples

### Example 1 Listing All Configurable Elements

This example lists all the configurable elements.

```
asadmin> list *
```

Output similar to the following is displayed:

```
applications
configs
configs.config.server-config
configs.config.server-config.admin-service
configs.config.server-config.admin-service.das-config
configs.config.server-config.admin-service.jmx-connector.system
configs.config.server-config.admin-service.property.adminConsoleContextRoot
configs.config.server-config.admin-service.property.adminConsoleDownloadLocation
configs.config.server-config.admin-service.property.ipsRoot
configs.config.server-config.ejb-container
configs.config.server-config.ejb-container.ejb-timer-service
configs.config.server-config.http-service
configs.config.server-config.http-service.access-log
configs.config.server-config.http-service.virtual-server._asadmin
configs.config.server-config.http-service.virtual-server.server
configs.config.server-config.iiop-service
configs.config.server-config.iiop-service.iiop-listener.SSL
configs.config.server-config.iiop-service.iiop-listener.SSL.ssl
configs.config.server-config.iiop-service.iiop-listener.SSL_MUTUALAUTH
configs.config.server-config.iiop-service.iiop-listener.SSL_MUTUALAUTH.ssl
configs.config.server-config.iiop-service.iiop-listener.orb-listener-1
configs.config.server-config.iiop-service.orb
configs.config.server-config.java-config
configs.config.server-config.jms-service
configs.config.server-config.jms-service.jms-host.default_JMS_host
configs.config.server-config.mdb-container
configs.config.server-config.monitoring-service
configs.config.server-config.monitoring-service.module-monitoring-levels
...
property.administrative.domain.name
resources
resources.jdbc-connection-pool.DerbyPool
resources.jdbc-connection-pool.DerbyPool.property.DatabaseName
resources.jdbc-connection-pool.DerbyPool.property.Password
resources.jdbc-connection-pool.DerbyPool.property.PortNumber
resources.jdbc-connection-pool.DerbyPool.property.User
resources.jdbc-connection-pool.DerbyPool.property.connectionAttributes
resources.jdbc-connection-pool.DerbyPool.property.serverName
resources.jdbc-connection-pool._TimerPool
resources.jdbc-connection-pool._TimerPool.property.connectionAttributes
resources.jdbc-connection-pool._TimerPool.property.databaseName
resources.jdbc-resource.jdbc/_TimerPool
resources.jdbc-resource.jdbc/_default
servers
servers.server.server
```

```
servers.server.server.resource-ref.jdbc/_TimerPool  
servers.server.server.resource-ref.jdbc/_default  
system-applications  
Command list executed successfully.
```

## Example 2 Listing All the Monitorable Objects

The following example lists all the monitorable objects.

```
asadmin> list --monitor *
```

Output similar to the following is displayed:

```
server  
server.jvm  
server.jvm.class-loading-system  
server.jvm.compilation-system  
server.jvm.garbage-collectors  
server.jvm.garbage-collectors.Copy  
server.jvm.garbage-collectors.MarkSweepCompact  
server.jvm.memory  
server.jvm.operating-system  
server.jvm.runtime  
server.network  
server.network.admin-listener  
server.network.admin-listener.connections  
server.network.admin-listener.file-cache  
server.network.admin-listener.keep-alive  
server.network.admin-listener.thread-pool  
server.network.http-listener-1  
server.network.http-listener-1.connections  
server.network.http-listener-1.file-cache  
server.network.http-listener-1.keep-alive  
server.network.http-listener-1.thread-pool  
server.transaction-service  
Command list executed successfully.
```

## See Also

[asadmin\(1M\)](#)

[get\(1\)](#), [list\(1\)](#), [set\(1\)](#)



# instance

An instance in Eclipse GlassFish has its own Jakarta EE configuration, Java EE resources, application deployment areas, and server configuration settings

## Description

Eclipse GlassFish creates one server instance, called `server` at the time of installation. You can delete the server instance and create a new instance with a different name.

For many users, one server instance meets their needs. However, depending upon your environment, you might want to create additional server instances. For example, in a development environment you can use different server instances to test different Eclipse GlassFish configurations, or to compare and test different application deployments. Because you can easily add or delete a server instance, you can use them to create temporary "sandbox" areas to experiment with while developing.

# logging

Capturing information on Eclipse GlassFish runtime events

## Description

Logging is the process by which Eclipse GlassFish captures data about events that occur during Eclipse GlassFish operation. Eclipse GlassFish components and application components generate logging data, which is saved in the server log, typically domain-dir`/logs/server.log`. The server log is the first source of information if Eclipse GlassFish problems occur.

The server log is rotated when the file reaches the specified size in bytes, or the specified time has elapsed. The file can also be rotated manually by using the [rotate-log](#) subcommand.

In addition to the server log, the domain-dir[/logs](#) directory contains two other kinds of logs:

- HTTP service access logs, located in the [/access](#) subdirectory
- Transaction service logs, located in the [/tx](#) subdirectory

Logging levels can be configured by using the Administration Console or the [set-log-levels](#) subcommand. Additional properties can be set by using the Administration Console or by editing the [logging.properties](#) file. The default [logging.properties](#) file is typically located in domain-dir[/config](#).

Although application components can use the Apache Commons Logging Library to record messages, the platform standard JSR 047 API is recommended for better log configuration.

## See Also

[list-log-levels\(1\)](#), [rotate-log\(1\)](#), [set-log-levels\(1\)](#)

[asadmin\(1M\)](#)

"[Administering the Logging Service](#)" in Eclipse GlassFish Administration Guide

# monitoring

Reviewing the runtime state of components and services deployed in Eclipse GlassFish

## Description

Monitoring is the process of reviewing the statistics of a system to improve performance or solve problems. By monitoring the state of various components and services deployed in Eclipse GlassFish, performance bottlenecks can be identified, failures can be anticipated, and runtime standards can be established and observed. Data gathered by monitoring can also be useful in performance tuning and capacity planning.

The Eclipse GlassFish monitoring service is enabled by default, that is, the `monitoring-enabled` attribute of the `monitoring-service` element is set to true. Once the monitoring service is enabled, a deployed module can then be enabled for monitoring by setting its monitoring level to HIGH or LOW (default is OFF). Monitoring can be configured dynamically by using the Administration Console or the `enable-monitoring` and the `disable-monitoring` subcommands. The `set` subcommand can also be used with dotted names to enable or disable monitoring. However, a server restart is required for changes made by using the `set` subcommand to take affect.

Monitoring data can be viewed by using the Administration Console or by using the subcommands of the `asadmin` utility.

- The `monitor` subcommand displays monitoring data for a given type, similar to the UNIX `top` command. The data is presented at given intervals.
- The `list` and `get` subcommands display comprehensive data. Both use dotted names to specify monitorable objects.

Alternate tools for monitoring Eclipse GlassFish components and services include JConsole and the REST interface.

The Monitoring Scripting Client or DTrace Monitoring can be used to start the available monitoring probes. Using these tools is helpful in identifying performance issues during runtime. Monitoring Scripting Client or DTrace Monitoring are only usable if their modules are present.

## See Also

[monitor\(1\)](#), [enable-monitoring\(1\)](#), [disable-monitoring\(1\)](#), [list\(1\)](#), [get\(1\)](#), [set\(1\)](#)

[dotted-names\(5ASC\)](#)

[asadmin\(1M\)](#)

"[Administering the Monitoring Service](#)" in Eclipse GlassFish Administration Guide



# passwords

Securing and managing Eclipse GlassFish

## Description

An administrator of Eclipse GlassFish manages one or more domains, each of which can have distinct administrative credentials. By managing a domain, an administrator effectively manages various resources like server instances, server clusters, libraries etc. that are required by the enterprise Java applications.

## See Also

[change-admin-password\(1\)](#), [change-master-password\(1\)](#), [create-password-alias\(1\)](#), [list-password-aliases\(1\)](#), [delete-password-alias\(1\)](#)

[asadmin\(1M\)](#)

# resource

Provide connectivity to various types of EIS.

## Description

Eclipse GlassFish provides support for JDBC, JMS, and JNDI resources.

## See Also

[asadmin\(1M\)](#)

# security

Secure and administer Eclipse GlassFish applications

## Description

Security is about protecting data: how to prevent unauthorized access or damage to it in storage or transit. Eclipse GlassFish has a dynamic, extensible security architecture based on the Jakarta EE standard. Built in security features include cryptography, authentication and authorization, and public key infrastructure. Eclipse GlassFish is built on the Java security model, which uses a sandbox where applications can run safely, without potential risk to systems or users.

## See Also

[change-admin-password\(1\)](#), [change-master-password\(1\)](#), [create-auth-realm\(1\)](#), [create-file-user\(1\)](#), [create-message-security-provider\(1\)](#), [create-password-alias\(1\)](#), [create-ssl\(1\)](#), [delete-auth-realm\(1\)](#), [delete-file-user\(1\)](#), [delete-message-security-provider\(1\)](#), [delete-password-alias\(1\)](#), [delete-ssl\(1\)](#), [list-auth-realms\(1\)](#), [list-connector-security-maps\(1\)](#), [list-file-groups\(1\)](#), [list-file-users\(1\)](#).

[asadmin\(1M\)](#)