LPI 109.3 - Basic network troubleshooting

Curs 2021 - 2022

ASIX M01-ISO 109 Networking Fundamentals

Basic network troubleshooting	2
Description	2
Network Tools	2
netstat Command	2
ss Command	3
Isof	4
ip command	5
ping command	8
traceroute command	g
tracepath command	10
ethtool command	10
netcat command	12
Network interface & Layers	12
Physical Layer	13
Data link layer	14
Network Layer	14
Transport Layer	18
Session & Presentation & Application Layers	18
Practical Example	18
Example Exercises	19

Basic network troubleshooting

Description

Key concepts:

- ☐ Manually configure network interfaces, including viewing and changing the configuration of network interfaces using iproute2.
- ☐ Manually configure routing, including viewing and changing routing tables and setting the default route using iproute2.
- ☐ Debug problems associated with the network configuration.
- Awareness of legacy net-tools commands.

Commands and files:

- ☐ ip
- hostname
- □ ss
- ping
- □ ping6
- □ traceroute
- ☐ traceroute6
- □ tracepath
- □ tracepath6
- □ netcat
- ifconfig
- □ netstat
- □ route

Network Tools

When troubleshooting a network, it is useful to gather information about networking services such as open ports, interface statistics, routing tables, and network connections. The following sections will cover common legacy and updated Linux tools available for displaying network status.

netstat Command

The netstat command is used by the system administrator to monitor the traffic on the network, and check connections that are not trustworthy.

- netstat
- netstat -s -r -i
- netstat -t -u -x -n -p -a
- netstat -l

```
$ netstat -tln
Active Internet connections (only servers)
Proto Recv-Q Send-Q Local Address
                                            Foreign Address
                                                                    State
         0 0 192.168.122.1:53
                                            0.0.0.0:*
                                                                    LISTEN
                0 127.0.0.1:631
0 :::80
tcp
           0
                                            0.0.0.0:*
                                                                    LISTEN
                                            :::*
tcp6
           0
                                                                    LISTEN
                                            :::*
tcp6
           0
                0 :::21
                                                                    LISTEN
tcp6
           0
                 0 ::1:631
                                            :::*
                                                                    LISTEN
```

```
$ netstat -u
Active Internet connections (w/o servers)
Proto Recv-Q Send-Q Local Address Foreign Address State
udp 0 0 mylaptop.edt.org:bootpc _gateway:bootps ESTABLISHED
```

Activ	e UNIX	domain so	ckets (w/o s	ervers)		
Proto	RefCnt	Flags	Type	State	I-Node	Path
unix	2	[]	DGRAM		51551	/run/user/1001/systemd/notify
unix	4	[]	DGRAM		16197	/run/systemd/notify
unix	23	[]	DGRAM		16209	/run/systemd/journal/dev-log
unix	16	[]	DGRAM		16213	/run/systemd/journal/socket
unix	2	[]	DGRAM		31327	/var/run/chrony/chronyd.sock
unix	2	[]	DGRAM		32379	/run/systemd/home/notify
unix	2	[]	DGRAM		87408	
@user	db-4e25	9eaec8a74	395f53e9d957	a38b841		
unix	2	[]	DGRAM		38053	@0000c

\$ netstat -i										
Kernel Interface	e table									
Iface	MTU	RX-OK	RX-ERR	RX-DRP	RX-OVR	TX-OK	TX-ERR	TX-DRP	TX-OVR	Flg
br-38fb360b0b9f	1500	0	0	0	0	0	0	0	0	BMU
docker0	1500	0	0	0	0	0	0	0	0	BMU
enp1s0	1500	0	0	0	0	0	0	0	0	BMU
10	65536	24	0	0	0	24	0	0	0	LRU
virbr0	1500	0	0	0	0	0	0	0	0	BMU
wlp0s20f3	1500	150012	0	0	0	76586	0	0	0	BMRU

ss Command

The ss command is designed to show socket statistics and supports all the major packet and socket types. Meant to be a replacement for and to be similar in function to the netstat command, it also shows a lot more information and has more features.

- SS
- SS -S
- ss -l -t -u -x

The output is very similar to the output of the netstat command with no options. The columns above are:

Netid - the socket type and transport protocol

State - Connected and Unconnected, depending on protocol

Recv-Q - Amount of data queued up for being processed having been received

Send-Q - Amount of data queued up for being sent to another host

Local Address - The address and port of the local host's portion of the connection Peer Address - The address and port of the remote host's portion of the connection

State	Recv-Q	Send-Q	Local Address:Port	Peer Addres	s:Port Process
ESTAB	0	0	192.168.1.45:54710	142.250.184.165:https	users:(("chrome",pid=3250,fd=40))
ESTAB	0	0	192.168.1.45:60586	5.79.35.160:https	users:(("chrome",pid=3250,fd=100))
ESTAB	0	0	192.168.1.45:59326	64.233.184.188:hpvroom	users:(("chrome",pid=3250,fd=46))
ESTAB	0	0	192.168.1.45:59968	142.250.200.142:https	users:(("chrome",pid=3250,fd=48))
ESTAB	0	0	192.168.1.45:53536	52.37.107.177:https	
ESTAB	0	0	192.168.1.45:41374	216.58.209.74:https	users:(("chrome",pid=3250,fd=67))
ESTAB	0	0	192.168.1.45:40838	64.233.166.189:https	users:(("chrome",pid=3250,fd=75))
ESTAB	0	0	192.168.1.45:57000	142.250.201.74:https	users:(("chrome",pid=3250,fd=39))
ESTAB	0	0	192.168.1.45:49906	142.250.184.174:https	users:(("chrome",pid=3250,fd=63))
ESTAB	0	0	192.168.1.45:52344	216.58.215.142:https	users:(("chrome",pid=3250,fd=57))
ESTAB	0	0	192.168.1.45:41000	142.250.200.131:https	users:(("chrome",pid=3250,fd=68))
ESTAB	0	0	192.168.1.45:41030	142.250.200.131:https	users:(("chrome",pid=3250,fd=85))

```
$ ss -s
Total: 1172
       21 (estab 11, closed 5, orphaned 0, timewait 1)
TCP:
Transport Total
                  ΙP
                               IPv6
         1
                    0
                              1
RAW
                   7
         10
                              3
UDP
TCP
         16
                   1.3
                              3
                              7
INET
         27
                    20
                              0
FRAG
```

Isof

```
$ lsof -i
COMMAND PID
                  USER
                           FD
                                 TYPE DEVICE SIZE/OFF NODE NAME
chrome 3203 ecanet chrome 3250 ecanet
                  136u IPv4 145006
27u IPv4 156056
                                       Ot0 UDP 224.0.0.251:mdns
Ot0 TCP mylaptop.edt.org:53178->208.94.166.201:https (ESTABLISHED)
chrome
       3250 ecanet
                   36u
                        IPv4 146201
                                       0t0
                                           TCP mylaptop.edt.org:36734->mad07s25-in-f14.1e100.net:https (ESTABLISHED) UDP mylaptop.edt.org:36520->mad41s14-in-f10.1e100.net:https
                    37u
       3250 ecanet
chrome
chrome 3250 ecanet
                   41u IPv4 156289
                                       0t0
                                           UDP mylaptop.edt.org:53681->mad07s25-in-f3.1e100.net:https
                                           UDP mylaptop.edt.org:57314->mad41s13-in-f14.1e100.net:https
chrome 3250 ecanet
                   45u IPv4 154078
# lsof -i | head
COMMAND
              PID
                      USER
                               FD
                                     TYPE DEVICE SIZE/OFF NODE NAME
avahi-dae
              817
                      avahi
                                15u
                                      IPv4
                                             31407
                                                           0t0
                                                                UDP *:mdns
avahi-dae
                                                           OtO UDP *:mdns
              817
                      avahi
                                16u
                                      IPv6
                                             31408
avahi-dae
              817
                     avahi
                                17u
                                     IPv4
                                             31409
                                                           0t0
                                                                 UDP *:52153
                                                           0t0 UDP *:50172
avahi-dae
              817
                      avahi
                                18u
                                     IPv6
                                             31410
chronyd
              864 chrony
                                 6u IPv4
                                            31324
                                                           0t0 UDP localhost:323
                                 7u
              864
                                             31325
                                                           0t0
                                                                 UDP localhost:323
chronyd
                    chrony
                                     IPv6
                               26u IPv4 146084
NetworkMa
              936
                                                           OtO UDP
                     root
mylaptop.edt.org:bootpc->_gateway:bootps
cupsd
              951
                      root
                                9u IPv6 36924
                                                           OtO TCP localhost:ipp (LISTEN)
cupsd
              951
                       root
                                10u IPv4 36925
                                                           OtO TCP localhost:ipp (LISTEN)
. . .
```

```
# lsof -i :22
COMMAND PID
                 USER
                         FD
                                TYPE DEVICE SIZE/OFF NODE NAME
       26415 root 5u IPv4 161929
                                           OtO TCP *:ssh (LISTEN)
OtO TCP *:ssh (LISTEN)
sshd
sshd
       26415
               root
                       7u IPv6 161931
       26547 ecanet
                       4u IPv6 160258
                                           OtO TCP localhost:57476->localhost:ssh (ESTABLISHED)
ssh
                                           OtO TCP localhost:ssh->localhost:57476 (ESTABLISHED)
       26548 root
                       5u IPv6 162091
sshd
                                           OtO TCP localhost:ssh->localhost:57476 (ESTABLISHED)
       26580 guest
                       5u IPv6 162091
sshd
```

ip command

The *ifconfig* command is becoming obsolete (deprecated) in some Linux distributions and is being replaced with a form of the *ip* command, specifically ip address.

- ip neighbor
- ip link
- ip address
- ip [-s]
- ip route

ip neigh

- ip neighbor show
- ip neighbor show dev <device>

```
$ ip neigh show
192.168.1.1 dev wlp0s20f3 lladdr e0:41:36:0e:5a:f0 REACHABLE
fe80::e241:36ff:fe0e:5af0 dev wlp0s20f3 lladdr e0:41:36:0e:5a:f0 router STALE

$ ip neigh show dev wlp0s20f3
192.168.1.1 lladdr e0:41:36:0e:5a:f0 REACHABLE
fe80::e241:36ff:fe0e:5af0 lladdr e0:41:36:0e:5a:f0 router STALE
```

```
$ arp
```

ip link

- ip link show
- ip link show dev device
- ip link set dev <device> up
- ip link set dev <device> down

```
$ ip link show
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode DEFAULT group
default qlen 1000
    link/loopback 00:00:00:00:00 brd 00:00:00:00:00
2: enp1s0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc fq_codel state DOWN mode
DEFAULT group default qlen 1000
    link/ether c0:18:50:14:97:b3 brd ff:ff:ff:ff:ff
3: wlp0s20f3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP mode
DORMANT group default qlen 1000
    link/ether 84:1b:77:00:78:c8 brd ff:ff:ff:ff:ff
4: virbr0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc noqueue state DOWN mode
```

```
DEFAULT group default qlen 1000
    link/ether 52:54:00:6c:e0:04 brd ff:ff:ff:ff:ff
5: virbr0-nic: <BROADCAST, MULTICAST> mtu 1500 qdisc fq codel master virbr0 state DOWN
mode DEFAULT group default glen 1000
    link/ether 52:54:00:6c:e0:04 brd ff:ff:ff:ff:ff
6: docker0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state DOWN mode
DEFAULT group default
   link/ether 02:42:f0:26:60:cf brd ff:ff:ff:ff:ff
7: br-38fb360b0b9f: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state
DOWN mode DEFAULT group default
    link/ether 02:42:4c:19:93:7c brd ff:ff:ff:ff:ff
$ ip -br link show
                 UNKNOWN
                                 00:00:00:00:00:00 < LOOPBACK, UP, LOWER UP>
10
                                 c0:18:50:14:97:b3 <NO-CARRIER, BROADCAST, MULTICAST, UP>
84:1b:77:00:78:c8 <BROADCAST, MULTICAST, UP, LOWER_UP>
enp1s0
                 DOMN
wlp0s20f3
                 IID
                 DOWN
                                 52:54:00:6c:e0:04 <NO-CARRIER, BROADCAST, MULTICAST, UP>
virbr0
virbr0-nic
                 DOWN
                                 52:54:00:6c:e0:04 <BROADCAST, MULTICAST>
                                 02:42:f0:26:60:cf <NO-CARRIER, BROADCAST, MULTICAST, UP>
                 DOMN
docker0
br-38fb360b0b9f DOWN
                                 02:42:4c:19:93:7c <NO-CARRIER, BROADCAST, MULTICAST, UP>
$ ip link show enp1s0
2: enpls0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc fq_codel state DOWN mode
DEFAULT group default qlen 1000
    link/ether c0:18:50:14:97:b3 brd ff:ff:ff:ff:ff
$ ip link show wlp0s20f3
3: wlp0s20f3: <BROADCAST,MULTICAST,UP,LOWER UP> mtu 1500 qdisc noqueue state UP mode
DORMANT group default qlen 1000
    link/ether 84:1b:77:00:78:c8 brd ff:ff:ff:ff:ff
```

```
[root@mylaptop ~]# ls /sys/class/net/
br-38fb360b0b9f docker0 enpls0 lo virbr0 virbr0-nic wlp0s20f3
```

```
# ip link set dev enp0s8 down
# ip link set dev enp0s8 up

# ip link set enp0s8 mtu 2000
# ifconfig enp0s3 mtu 1500

# ip link show dev enp0s8
```

ip address

- ip address show
- ip address show dev <device>
- ip address add ip/mask dev <device>
- ip address del ip/mask dev <device>

```
default glen 1000
    link/ether 84:1b:77:00:78:c8 brd ff:ff:ff:ff:ff
    inet 192.168.1.45/24 brd 192.168.1.255 scope global dynamic noprefixroute wlp0s20f3
       valid 1ft 39380sec preferred 1ft 39380sec
    inet6 fe80::2062:d7b2:5a59:f895/64 scope link noprefixroute
       valid lft forever preferred lft forever
4: virbr0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state DOWN group
default glen 1000
    link/ether 52:54:00:6c:e0:04 brd ff:ff:ff:ff:ff
    inet 192.168.122.1/24 brd 192.168.122.255 scope global virbr0
       valid lft forever preferred lft forever
5: virbr0-nic: <BROADCAST, MULTICAST> mtu 1500 qdisc fq codel master virbr0 state DOWN
group default qlen 1000
   link/ether 52:54:00:6c:e0:04 brd ff:ff:ff:ff:ff
6: docker0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state DOWN group
default
    link/ether 02:42:f0:26:60:cf brd ff:ff:ff:ff:ff
    inet 172.17.0.1/16 brd 172.17.255.255 scope global docker0
       valid_lft forever preferred lft forever
7: br-38fb360b0b9f: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state
DOWN group default
    link/ether 02:42:4c:19:93:7c brd ff:ff:ff:ff:ff
    inet 192.168.49.1/24 brd 192.168.49.255 scope global br-38fb360b0b9f
       valid lft forever preferred lft forever
$ ip addr show wlp0s20f3
3: wlp0s20f3: <BROADCAST,MULTICAST,UP,LOWER UP> mtu 1500 qdisc noqueue state UP group
default glen 1000
    link/ether 84:1b:77:00:78:c8 brd ff:ff:ff:ff:ff
    inet 192.168.1.45/24 brd 192.168.1.255 scope global dynamic noprefixroute wlp0s20f3
    valid_lft 39344sec preferred lft 39344sec
inet6 fe80::2062:d7b2:5a59:f895/64 scope link noprefixroute
       valid lft forever preferred lft forever
$ ip addr show docker0
6: docker0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state DOWN group
default
    link/ether 02:42:f0:26:60:cf brd ff:ff:ff:ff:ff
    inet 172.17.0.1/16 brd 172.17.255.255 scope global docker0
       valid_lft forever preferred lft forever
```

```
# ip addr add 192.168.5.5/24 dev enp0s8
# ip addr add 2001:db8::10/64 dev enp0s8
```

```
# ifconfig eth2 192.168.50.50 netmask 255.255.255.0
# ifconfig eth2 192.168.50.50 netmask 0xfffffff00
# ifconfig enp0s8 add 2001:db8::10/64
```

ip route

- ip route show
- ip route add net/mask dev <device>
- ip route del net/mask dev <device>
- ip route add default via ip-gateway
- ip route del default via ip-gateway

The output of ip route and ip -6 route reads as follows:

- Destination.
- Optional address followed by interface.
- The routing protocol used to add the route.

- The scope of the route. If this is omitted, it is global scope, or a gateway.
- The route's metric. This is used by dynamic routing protocols to determine the cost of the route. This isn't used by most systems.
- If it is an IPv6 route, the RFC4191 route preference.

```
$ ip route show
default via 192.168.1.1 dev wlp0s20f3 proto dhcp metric 600
172.17.0.0/16 dev docker0 proto kernel scope link src 172.17.0.1 linkdown
192.168.1.0/24 dev wlp0s20f3 proto kernel scope link src 192.168.1.45 metric 600
192.168.49.0/24 dev br-38fb360b0b9f proto kernel scope link src 192.168.49.1 linkdown
192.168.122.0/24 dev virbr0 proto kernel scope link src 192.168.122.1 linkdown
```

```
$ netstat -r
$ ip route
$ route
```

```
# ip route add 192.68.10..0/24 dev enp1s8

# ip route del 192.168.10.0/24 dev enp1s8

# ip route add default via 192.168.1.1

# ip route del default via 192.168.1.1
```

ping command

The packet internet groper ping command is used to check the connectivity to a host. It is a simple test that can be performed from the command prompt when a particular network service is not available. This utility sends the ICMP protocol's ECHO_REQUEST (ping) datagram to a host, and the host sends an ECHO_RESPONSE (pong) datagram in response. Each datagram will have an IP header, an ICMP header, a timeval structure, and some additional bytes used for padding.

The Time To Live (TTL) value is the maximum number of IP routers that may attempt to route a packet. Every time a router attempts to route the packets, its TTL count is decremented by 1. If a router receives a packet and the TTL of a packet is zero, then the packet is discarded.

- ping
- ping -c

Some of the ping options:

-c count Stop after sending count ECHO_REQUEST packets -s packetsize Specifies the number of data bytes to be sent

-t ttl Sets the IP Time to Live

-w timeout Sets the timeout in seconds for ping to exit

The ping6 command is similar to the ping command, but it uses ICMPv6 ECHO_REQUEST to verify network connectivity. The ping6 command can use either a hostname or an IPv6

```
$ ping www.google.com
PING www.google.com (142.250.201.68) 56(84) bytes of data.
64 bytes from mad07s25-in-f4.1e100.net (142.250.201.68): icmp_seq=1 ttl=115 time=13.3 ms
64 bytes from mad07s25-in-f4.1e100.net (142.250.201.68): icmp_seq=2 ttl=115 time=10.7 ms
^C
--- www.google.com ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 1002ms
rtt min/avg/max/mdev = 10.701/11.997/13.294/1.296 ms

$ ping6 www.google.com
ping6: connect: Network is unreachable
$ ping google.com
PING google.com (172.217.17.14) 56(84) bytes of data.
64 bytes from mad07s09-in-f14.1e100.net (172.217.17.14): icmp_seq=1 ttl=115 time=9.99 ms
64 bytes from mad07s09-in-f14.1e100.net (172.217.17.14): icmp_seq=2 ttl=115 time=11.6 ms
^C64 bytes from 172.217.17.14: icmp_seq=3 ttl=115 time=170 ms
--- google.com ping statistics ---
3 packets transmitted, 3 received, 0% packet loss, time 2003ms
rtt min/avg/max/mdev = 9.988/63.995/170.409/75.248 ms
```

traceroute command

The traceroute command is used to trace the route of packets to a specified host. This utility uses the IP header's TTL field and tries to fetch an ICMP TIME_EXCEEDED response from each router on the path to the host. The probing is done by sending ICMP ping packets with a small TTL value and then checking the ICMP TIME_EXCEEDED response.

The traceroute command, commonly used for seeing how a transmission travels between a local host machine to a remote system

```
-T Probe using TCP SYN

-f first_ttl Specifies the initial TTL value

-m max_ttl Specifies the maximum number of hops to be probed

-w timeout Sets the timeout in seconds to exit after waiting for a response to a probe
```

```
$ traceroute lms.pue.es
traceroute to lms.pue.es (51.15.184.105), 30 hops max, 60 byte packets
     gateway (192.168.1.1) 1.767 ms 1.934 ms 3.208 ms
    136.red-81-46-38.customer.static.ccgg.telefonica.net (81.46.38.136) 6.596 ms 7.362
    7.557 ms
 3 33.red-81-46-34.customer.static.ccqq.telefonica.net (81.46.34.33) 9.070 ms 9.029
    12.602 ms
   * be8-400-grtbcnes1.net.telefonicaglobalsolutions.com (213.140.50.218) 3.524 ms *
   176.52.248.191 (176.52.248.191) 10.713 ms 14.024 ms 11.253 ms 176.52.248.172 (176.52.248.172) 15.666 ms 176.52.248.174 (176.52.248.174)
                                         15.666 ms 176.52.248.174 (176.52.248.174) 16.119
ms 176.52.248.172 (176.52.248.172) 16.308 ms
 9 176.52.248.178 (176.52.248.178) 17.559 ms lag-34.earl.Madridl.Level3.net
(4.68.39.69) 24.611 ms 14.123 ms
10 * * *
11
   212.3.235.198 (212.3.235.198) 24.855 ms ae-5.edge1.Madrid2.Level3.net (4.68.39.33)
12.252 ms 13.188 ms
12 51.158.8.71 (51.158.8.71) 25.369 ms 28.165 ms 24.423 ms 13 212.3.235.198 (212.3.235.198) 25.134 ms 26.505 ms 26.467 ms
```

```
$ traceroute labs.pue.es
traceroute to labs.pue.es
traceroute to labs.pue.es (212.83.191.190), 30 hops max, 60 byte packets

1 _gateway (192.168.1.1) 1.508 ms 1.849 ms 2.695 ms
2 136.red-81-46-38.customer.static.ccgg.telefonica.net (81.46.38.136) 7.717 ms 7.955
ms 9.074 ms
3 33.red-81-46-34.customer.static.ccgg.telefonica.net (81.46.34.33) 11.196 ms 11.169
ms 11.141 ms
4 133.red-81-46-34.customer.static.ccgg.telefonica.net (81.46.34.133) 24.399 ms
24.372 ms 24.344 ms
5 46.red-80-58-81.staticip.rima-tde.net (80.58.81.46) 12.660 ms 12.913 ms 13.601 ms
6 213.140.50.204 (213.140.50.204) 15.109 ms 3.606 ms 6.140 ms
...
```

tracepath command

The tracepath command is used to trace the path to a network host, discovering MTU (maximum transmission unit) along the path. The functionality is similar to traceroute. It sends ICMP and UDP messages of various sizes to find the MTU size on the path. Using UDP messages to trace the path can be useful when routers are configured to filter ICMP traffic.

```
$ tracepath lms.pue.es
 1?: [LOCALHOST]
                                            pmtu 1500
 1: _gateway
1: _gateway
                                                                     4.125ms
                                                                     6.719ms
                                                                     7.006ms pmtu 1492
      gateway
 2: 136.red-81-46-38.customer.static.ccgg.telefonica.net 14.672ms
 3: 33.red-81-46-34.customer.static.ccgg.telefonica.net 8.155ms asymm 8
4: no reply
 5: no reply
 6: be8-400-grtbcnes1.net.telefonicaglobalsolutions.com 11.160ms asymm 7: 176.52.248.191 13.968ms asymm
8: 5.53.6.64
9: lag-34.earl.Madrid1.Level3.net
10: 176.52.248.247
                                                                    69.992ms asymm
                                                                    17.411ms asymm
                                                                    18.191ms asymm
11: 212.3.235.198
12: 51.158.8.71
                                                                    27.129 \mathrm{ms} asymm 10
                                                                    31.315ms asymm 11
13: 212.3.235.198
                                                                    26.832ms asymm 10
14:
     51.158.8.71
                                                                    27.029ms asymm 11
15: 195.154.2.7
                                                                    28.436ms asymm 11
16: siurana.pue.es
                                                                    25.865ms !H
     Resume: pmtu 1492
```

ethtool command

The ethtool utility is useful for configuring and troubleshooting network devices such as Ethernet cards and their device drivers, and other useful troubleshooting information, such as the speed of an interface.

```
$ ethtool enp1s0
Settings for enp1s0:
    Supported ports: [ TP MII ]
```

```
Supported link modes:
                               10baseT/Half 10baseT/Full
                               100baseT/Half 100baseT/Full
                               1000baseT/Full
       Supported pause frame use: Symmetric Receive-only
       Supports auto-negotiation: Yes
       Supported FEC modes: Not reported
       Advertised link modes: 10baseT/Half 10baseT/Full
                               100baseT/Half 100baseT/Full
                               1000baseT/Full
       Advertised pause frame use: Symmetric Receive-only
       Advertised auto-negotiation: Yes
       Advertised FEC modes: Not reported
       Speed: Unknown!
       Duplex: Unknown! (255)
       Auto-negotiation: on
       master-slave cfg: preferred slave
       master-slave status: unknown
       Port: Twisted Pair
       PHYAD: 0
       Transceiver: external
       MDI-X: Unknown
netlink error: Operation not permitted
       Link detected: no
```

```
$ ethtool -i enpls0
driver: r8169
version: 5.11.22-100.fc32.x86_64
firmware-version: rtl8168h-2_0.0.2 02/26/15
expansion-rom-version:
bus-info: 0000:01:00.0
supports-statistics: yes
supports-test: no
supports-eeprom-access: no
supports-register-dump: yes
supports-priv-flags: no
```

```
$ ethtool -i wlp0s20f3
driver: iwlwifi
version: 5.11.22-100.fc32.x86_64
firmware-version: 59.601f3a66.0 Qu-c0-hr-b0-59.uc
expansion-rom-version:
bus-info: 0000:00:14.3
supports-statistics: yes
supports-test: no
supports-eeprom-access: no
supports-eprom-access: no
supports-priv-flags: no

# ethtool wlp0s20f3
Settings for wlp0s20f3:
    Link detected: yes
```

```
virbr0-nic no wireless extensions.

docker0 no wireless extensions.

br-38fb360b0b9f no wireless extensions.
```

```
$ iwconfig wlp0s20f3
wlp0s20f3 IEEE 802.11 ESSID:"MOVISTAR_5AF0"
Mode:Managed Frequency:2.437 GHz Access Point: E2:41:36:0E:5A:F0
Bit Rate=48 Mb/s Tx-Power=22 dBm
Retry short limit:7 RTS thr:off Fragment thr:off
Power Management:on
Link Quality=51/70 Signal level=-59 dBm
Rx invalid nwid:0 Rx invalid crypt:0 Rx invalid frag:0
Tx excessive retries:38 Invalid misc:22 Missed beacon:0
```

netcat command

The netcat utility is a cross-platform tool that can be used for monitoring and debugging network connections. The netcat command can also be used in the short form neat or ne.

```
$ netcat -z localhost 1-100
Connection to localhost (::1) 21 port [tcp/ftp] succeeded!
Connection to localhost (::1) 80 port [tcp/http] succeeded!
$ netcat -zv localhost 1-100
...
```

```
(host1)$ sudo netcat -1 5001
(host2)$ netcat host1 5001
```

```
(tty1)$ sudo netcat -1 5001
(tty2)$ netcat localhost 5001
```

```
$ netcat smtp.gmail.com 25
220 smtp.gmail.com ESMTP be3sm596522wmb.1 - gsmtp
EHLO
501-5.5.4 Empty HELO/EHLO argument not allowed, closing connection.
501 5.5.4 https://support.google.com/mail/?p=helo be3sm596522wmb.1 - gsmtp
...
```

Network interface & Layers

OSI network layers:

7 Application

6 Presentation

- 5 Session
- 4 Transport
- 3 Network
- 2 Data-Link
- 1 Physical

Physical Layer

The physical layer of the OSI model defines hardware connections and turns binary data into physical pulses (electrical, light, or radio waves).

"Is the device on?", "Is my network card detected?", and "Is the network card connected?"

- Ispci
- Isusb
- Ismod
- ip link show

```
# lspci | grep -E "Network|Ethernet"
00:14.3 Network controller: Intel Corporation Killer Wi-Fi 6 AX1650i 160MHz Wireless
Network Adapter (201NGW) (rev 30)
01:00.0 Ethernet controller: Realtek Semiconductor Co., Ltd. RTL8111/8168/8411 PCI
Express Gigabit Ethernet Controller (rev 15)
# lspci -vs 00:14.3
00:14.3 Network controller: Intel Corporation Killer Wi-Fi 6 AX1650i 160MHz Wireless
Network Adapter (201NGW) (rev 30)
       Subsystem: Intel Corporation Device 0074
       Flags: bus master, fast devsel, latency 0, IRQ 16
       Memory at 81430000 (64-bit, non-prefetchable) [size=16K]
       Capabilities: [c8] Power Management version 3
       Capabilities: [d0] MSI: Enable- Count=1/1 Maskable- 64bit+
       Capabilities: [40] Express Root Complex Integrated Endpoint, MSI 00
       Capabilities: [80] MSI-X: Enable+ Count=16 Masked-
       Capabilities: [100] Latency Tolerance Reporting
       Capabilities: [164] Vendor Specific Information: ID=0010 Rev=0 Len=014 <?>
       Kernel driver in use: iwlwifi
       Kernel modules: iwlwifi
# lspci -vs 01:00.0
01:00.0 Ethernet controller: Realtek Semiconductor Co., Ltd. RTL8111/8168/8411 PCI
Express Gigabit Ethernet Controller (rev 15)
       Subsystem: Lenovo Device 3852
        Flags: bus master, fast devsel, latency 0, IRQ 16
       I/O ports at 2000 [size=256]
       Memory at 81304000 (64-bit, non-prefetchable) [size=4K]
Memory at 81300000 (64-bit, non-prefetchable) [size=16K]
       Capabilities: [40] Power Management version 3
       Capabilities: [50] MSI: Enable- Count=1/1 Maskable- 64bit+
       Capabilities: [70] Express Endpoint, MSI 01
       Capabilities: [b0] MSI-X: Enable+ Count=4 Masked-
       Capabilities: [100] Advanced Error Reporting
       Capabilities: [140] Virtual Channel
       Capabilities: [160] Device Serial Number 00-00-00-00-00-00 Capabilities: [170] Latency Tolerance Reporting
       Capabilities: [178] L1 PM Substates
       Kernel driver in use: r8169
       Kernel modules: r8169
```

```
# modinfo r8169
```

modinfo iwlwifi

```
$ ip link show dev enpls0
2: enpls0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc fq_codel state DOWN mode
DEFAULT group default qlen 1000
        link/ether c0:18:50:14:97:b3 brd ff:ff:ff:ff:
$ ip link show dev wlp0s20f3
3: wlp0s20f3: <BROADCAST, MULTICAST, UP, LOWER_UP> mtu 1500 qdisc noqueue state UP mode
DORMANT group default qlen 1000
        link/ether 84:1b:77:00:78:c8 brd ff:ff:ff:ff:ff
```

```
# ip link set eth0 up
# ip link set eth0 down
```

Data link layer

The data-link layer of the OSI model defines the interface to the physical layer. It also monitors and corrects for errors that may occur in the physical layer by using a frame check sequence (FCS). The data-link layer keeps a table of IP address to MAC address translations.

"Does this computer see any devices on the network?"

- ip neighbor
- ethtool
- arp [-a]

Network Layer

The network layer of the OSI model performs network routing functions, defines logical addresses, and uses a hierarchical addressing scheme. Various protocols specify packet structure and processing used to carry data from host to host.

"Does this device have an IP address?" and "Is the gateway address set on this device?"

- ip address
- ip route
- dhclient -v etho
- dhclient -r eth0

```
$ ip addr show lo
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen
1000
    link/loopback 00:00:00:00:00 brd 00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever

# ip a show docker0
6: docker0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc noqueue state DOWN group default
    link/ether 02:42:f0:26:60:cf brd ff:ff:ff:ff:
    inet 172.17.0.1/16 brd 172.17.255.255 scope global docker0
    valid_lft forever preferred_lft forever
```

```
# dhclient -v wlp0s20f3
Internet Systems Consortium DHCP Client 4.4.2b1
Copyright 2004-2019 Internet Systems Consortium.
All rights reserved.
For info, please visit https://www.isc.org/software/dhcp/

Listening on LPF/wlp0s20f3/84:1b:77:00:78:c8
Sending on LPF/wlp0s20f3/84:1b:77:00:78:c8
Sending on Socket/fallback
DHCPDISCOVER on wlp0s20f3 to 255.255.255.255 port 67 interval 3 (xid=0xd6cb6850)
DHCPOFFER of 192.168.1.45 from 192.168.1.1
DHCPREQUEST for 192.168.1.45 on wlp0s20f3 to 255.255.255.255 port 67 (xid=0xd6cb6850)
DHCPACK of 192.168.1.45 from 192.168.1.1 (xid=0xd6cb6850)
bound to 192.168.1.45 -- renewal in 19339 seconds.
```

Routing Table

When checking network connectivity, ensure that your system can get to the assigned gateway. The network gateway, as defined in your network interface configuration, is the "first hop" or the first place your computer will go to when looking for resources beyond the local network.

```
$ ip route
default via 192.168.1.1 dev wlp0s20f3 proto dhcp metric 600
172.17.0.0/16 dev docker0 proto kernel scope link src 172.17.0.1 linkdown
192.168.1.0/24 dev wlp0s20f3 proto kernel scope link src 192.168.1.45 metric 600
192.168.49.0/24 dev br-38fb360b0b9f proto kernel scope link src 192.168.49.1 linkdown
192.168.122.0/24 dev virbr0 proto kernel scope link src 192.168.122.1 linkdown
```

Domain Name System

Beyond network connectivity, uniform resource locator (URL) addresses need to be resolved to IP addresses using DNS.

- nslookup
- host
- dig
- /etc/hosts
- /etc/resolv.conf

```
# cat /etc/hosts
127.0.0.1 localhost localhost.localdomain localhost4 localhost4.localdomain4
::1 localhost localhost.localdomain localhost6 localhost6.localdomain6
192.168.122.28 centos20

# cat /etc/resolv.conf
; generated by /usr/sbin/dhclient-script
search Home edt.org
nameserver 80.58.61.250
nameserver 80.58.61.254
```

Firewalls

Linux uses IP tables to manage network traffic, and in RH systems firewalld.

- ipchains (old)
- iptables
- ip6tables
- firewalld

```
# iptables -L -t nat
Chain PREROUTING (policy ACCEPT)
target prot opt source destination
DOCKER all -- anywhere anywhere ADDRTYPE match dst-type
LOCAL
```

```
Chain INPUT (policy ACCEPT)
target
             prot opt source
                                                       destination
Chain OUTPUT (policy ACCEPT)
target prot opt source
                                                       destination
                                                    !127.0.0.0/8
                                                                                   ADDRTYPE match dst-type
DOCKER
              all -- anywhere
LOCAL
Chain POSTROUTING (policy ACCEPT)
target prot opt source destination
MASQUERADE all -- 172.17.0.0/16 anywhere
MASQUERADE all -- 192.168.49.0/24 anywhere
LIBVIRT_PRT all -- anywhere anywhere
                                                     destination
                                                        anywhere
Chain DOCKER (2 references)
           prot opt source
target
                                                      destination
             all -- anywhere all -- anywhere
RETURN
                                                     anywhere
RETURN
                                                       anywhere
Chain LIBVIRT PRT (1 references)
           prot opt source
                                                       destination
RETURN all -- 192.168.122.0/24 base-address.mcast.net/24
RETURN all -- 192.168.122.0/24 255.255.255
MASQUERADE tcp -- 192.168.122.0/24 !192.168.122.0/24 mass
                                                                                     masq ports: 1024-65535
MASQUERADE udp -- 192.168.122.0/24 !192.168.122.0/24 masq ports: 1024-65535 MASQUERADE all -- 192.168.122.0/24 !192.168.122.0/24
```

up/down and delete interfaces

The ifup and ifdown legacy commands are used to bring up and bring down a network interface, respectively. Now the ip link command is used.

- ifup [deprecated]
- ifdown [deprecated
- ip link set eth0 up
- ip link set eth0 down

```
# ip link set dev eth0 down
```

To delete an interface and make the change permanent, the configuration file for the corresponding interface should be deleted. After modifying the file the networking service should be restarted

- /etc/sysconfig/network-scripts/ifcfg-eth1 (Red Hat)
- /etc/network/interfaces

```
# rm /etc/sysconfig/network-scripts/ifcfg-eth1
```

Transport Layer

The transport layer of the OSI model performs transparent transfer of data between end users. It is responsible for error recovery and flow control and ensures complete data transfer.

To find out if the service is running and if it can be reached use the commands:

- SS
- netstat
- nmap
- ncat

```
# nmap localhost
Starting Nmap 7.80 ( https://nmap.org ) at 2021-11-15 20:48 CET
Nmap scan report for localhost (127.0.0.1)
Host is up (0.0000040s latency).
Other addresses for localhost (not scanned): ::1
Not shown: 997 closed ports
PORT STATE SERVICE
21/tcp open ftp
80/tcp open http
631/tcp open ipp
```

Session & Presentation & Application Layers

The session, presentation, and application layers of the OSI model are all handled by software.

To get a good look at the inner workings of network communications, capture some data using tcpdump, iptrace or Wireshark.

Practical Example

PUE labs:

- Centos 172.16.5.1/24 ens3Debian 172.16.5.2/24 dev ens3
- 1. Debian

```
[ assign a new IP to the ens3 interface ]

ip address add 10.0.0.1/8 dev ens3

ip r
```

2. Centos

[assign a new IP to the ens3 interface]

```
ip address add 10.0.0.2/8 dev ens3
ping 10.0.0.2
ping 10.0.0.1
ip r
```

[now debian and centos share the network 10.0.0.0/8]

3. Debian

```
[ activate routing, now debian acts as a router ]
```

```
sysctl net.ipv4.ip forward=1
```

4. Centos

[configure in centos the gateway, now the gateway is debian]
[external connections arrive to debian and outer, but they don't return because are

```
ip route add default via 10.0.0.1
ping 8.8.8.8
ping labs.pue.es
traceroute 8.8.8.8
```

private addresses and router debian don't do NAT]

5. Debian

[configure router Debian to do NAT]

```
iptables .t nat -A POSTROUTING -s 10.0.0.0/8 -o ens3 -j MASQUERADE
```

6. Centos

[Verify now centos has full internet acces]

```
host 8.8.8.8
host labs.pue.es
ip route del 172.16.5.0/24 dev ens3
ip r
traceroute 8.8.8.8
```

Example Exercises

- 1. Which commands can be used to list network interfaces?
- 2. How would you temporarily disable an interface? How would you re-enable it?
- 3. Which commands can you use to show the default route?
- 4. How would you add a second IP address to an interface?
- 5. How would you configure a default route?
- 6. Which command(s) would you use to send an ICMP echo to learning.lpi.org?
- 7. How could you determine the route to 8.8.8.8?
- 8. Which command shows you if any processes are listening on TCP port 80?
- 9. How could you determine the max MTU of the network path to 1.1.1.1?

- 10. Realitza els exercicis indicats a: 109.3 Basic network troubleshooting
- 11. Realitza els exercicis del Question-Topics 108.3