LPI 102.3- Control mounting and unmounting filesystems

Curs 2021 - 2022

ASIX M01-ISO

Control mounting and umounting filesystems	2
Description	2
Mounting filesystems	2
Automatically mounting filesystems on boot: fstab	7
Systemd mount units	9
Examples	10
Example exercices	10

Control mounting and umounting filesystems

Description

Key concepts:

- ☐ Manually mount and unmount filesystems.
- onfigure filesystem mounting on bootup.
- □ Configure user mountable removable filesystems.
- ☐ Use of labels and UUIDs for identifying and mounting file systems.
- Awareness of systemd mount units.

Commands anf files:

- ☐ /etc/fstab
- ☐ /media/
- ☐ mount
- □ umount
- □ blkid
- ☐ Isblk
- □ Isof
- fuser

Mounting filesystems

Recall the three steps in the process of making and using filesystems:

- 1. Divide the hard drive into partitions.
- 2. Format each partition with a filesystem.
- 3. Mount the formatted partitions onto the directory tree of an existing filesystem.

Show pptions:

- mount. Shows all the mounted filesystems
- mount -t fstype show all the mounted fstype filesystems

```
device mountpoint fstype options
```

```
$ mount -t ext4
/dev/mapper/fedora-root on / type ext4 (rw,relatime,seclabel)
/dev/nvme0n1p2 on /boot type ext4 (rw,relatime,seclabel)
/dev/mapper/fedora-home on /home type ext4 (rw,relatime,seclabel)
$ mount -t proc
```

```
proc on /proc type proc (rw,nosuid,nodev,noexec,relatime)

$ mount -t tmpfs
tmpfs on /dev/shm type tmpfs (rw,nosuid,nodev,seclabel,inode64)
tmpfs on /run type tmpfs (rw,nosuid,nodev,seclabel,mode=755,inode64)
tmpfs on /tmp type tmpfs (rw,nosuid,nodev,seclabel,inode64)
tmpfs on /run/user/1001 type tmpfs
(rw,nosuid,nodev,relatime,seclabel,size=764812k,mode=700,uid=1001,gid=1001,inode64)

# mount
```

Manual mount / umount

- directory mountpoint must exist
- contents of the original directory will be masked (not visible until unmounted)
- /mnt usual mount point
- /media mount point for removible media used by graphical desktops.
- Options
 - -t fstype
 - o -o options
 - o options: rw, ro, remount, user, users, noauto, loop
 - fstype: ext4 etx3, xfs, vfat, msdos, auto
- umount
 - o umount device
 - umount mountpoint
 - umount device mountpoint

```
# mount /dev/sdb1 /imatges
```

Example:

- create raw virtual partitions
- format the partitions
- mount/umount the partitions

```
# dd if=/dev/zero of=linux.img bs=1k count=200K
204800+0 records in
204800+0 records out
209715200 bytes (210 MB, 200 MiB) copied, 0.362003 s, 579 MB/s
# dd if=/dev/zero of=windows.img bs=1k count=200K
204800+0 records in
204800+0 records out
209715200 bytes (210 MB, 200 MiB) copied, 0.258256 s, 812 MB/s
# dd if=/dev/zero of=swap.img bs=1k count=200K
204800+0 records in
204800+0 records out
209715200 bytes (210 MB, 200 MiB) copied, 0.248884 s, 843 MB/s
# dd if=/dev/zero of=xfs.img bs=1k count=200K
204800+0 records in
204800+0 records out
209715200 bytes (210 MB, 200 MiB) copied, 0.253501 s, 827 MB/s
```

```
# mkfs -t ext4 linux.img
mke2fs 1.45.5 (07-Jan-2020)
Discarding device blocks: done
Creating filesystem with 204800 1k blocks and 51200 inodes
Filesystem UUID: c2e64874-2258-492d-8954-0fa7643b8c10
Superblock backups stored on blocks:
       8193, 24577, 40961, 57345, 73729
Allocating group tables: done
Writing inode tables: done
Creating journal (4096 blocks): done
Writing superblocks and filesystem accounting information: done
# mkfs -t vfat windows.img
mkfs.fat 4.1 (2017-01-24)
# mkswap swap.img
mkswap: swap.img: insecure permissions 0644, 0600 suggested.
Setting up swapspace version 1, size = 200 MiB (209711104 bytes)
no label, UUID=6b9f8511-101d-4aa9-889e-953ada153530
# chmod 600 swap.img
# mkswap swap.img
mkswap: swap.img: warning: wiping old swap signature.
Setting up swapspace version 1, size = 200 MiB (209711104 bytes)
no label, UUID=e6a213d6-67fa-4ec0-928c-b0f9b493756e
# mkfs -t xfs xfs.img
meta-data=xfs.img
                                 isize=512
                                              agcount=4, agsize=12800 blks
                                 sectsz=512
                                              attr=2, projid32bit=1
                                              finobt=1, sparse=1, rmapbt=0
                                 crc=1
                                 reflink=1
         =
                                 hsize=4096
                                              blocks=51200, imaxpct=25
        =
data
                                 sunit=0
                                              swidth=0 blks
        =version 2
                                 bsize=4096
                                              ascii-ci=0, ftype=1
log
        =internal log
                                bsize=4096
                                              blocks=1368, version=2
                                 sect.sz=512
                                              sunit=0 blks, lazy-count=1
realtime =none
                                 extsz=4096
                                              blocks=0, rtextents=0
```

```
#3
# file *.img
disk.img: DOS/MBR boot sector; partition 1 : ID=0xee, start-CHS (0x0,0,2), end-CHS
(0x15,21,16), startsector 1, 4194303 sectors
linux.img: Linux rev 1.0 ext4 filesystem data,
UUID=c2e64874-2258-492d-8954-0fa7643b8c10 (extents) (64bit) (large files) (huge files)
swap.img: Linux/i386 swap file (new style), version 1 (4K pages), size 51199 pages,
no label, UUID=e6a213d6-67fa-4ec0-928c-b0f9b493756e
windows.img: DOS/MBR boot sector, code offset 0x3c+2, OEM-ID "mkfs.fat", sectors/cluster
8, reserved sectors 8, root entries 512, Media descriptor 0xf8, sectors/FAT 200,
sectors/track 32, heads 64, sectors 409600 (volumes > 32 MB), serial number 0xb3fa37cf,
unlabeled, FAT (16 bit)
xfs.img: SGI XFS filesystem data (blksz 4096, inosz 512, v2 dirs)
```

```
#4
# mount linux.img /mnt/
# ls /mnt/
lost+found

# echo "linux fs" > /mnt/message.txt

# mount -t ext4
/dev/mapper/fedora-root on / type ext4 (rw,relatime,seclabel)
/dev/nvme0n1p2 on /boot type ext4 (rw,relatime,seclabel)
/dev/mapper/fedora-home on /home type ext4 (rw,relatime,seclabel)
/home/images/VM/linux.img on /mnt type ext4 (rw,relatime,seclabel)
```

```
# mount windows.img /mnt
# mount -t vfat
/dev/nvme0n1p1 on /boot/efi type vfat
(rw,relatime,fmask=0077,dmask=0077,codepage=437,iocharset=ascii,shortname=winnt,errors=r
emount-ro)
/home/images/VM/windows.img on /mnt type vfat
(rw,relatime,fmask=0022,dmask=0022,codepage=437,iocharset=ascii,shortname=mixed,errors=r
emount-ro)
# umount windows.img
# mount -t xfs -o ro xfs.img /mnt/
# mount -t xfs
/home/images/VM/xfs.img on /mnt type xfs
(ro, relatime, seclabel, attr2, inode64, logbufs=8, logbsize=32k, noquota)
# echo "fstype xfs" > /mnt/message.txt
-bash: /mnt/message.txt: Read-only file system
# umount /mnt
# swapon swap.img
# swapon -s
Filename
                                                   Size Used Priority
                                     Type
                                            partition
                                                           7811068 5640 -2
204796 0 -3
/dev/dm-1
/home/images/VM/swap.img
                                             file
                                                           204796 0
# swapoff swap.img
# swapon -s
                                                                 Priority
Filename
                                     Type
                                                    Size
                                                           Used
/dev/dm-1
                                            partition
                                                           78110684868
```

```
# create an iso image
$ mkisofs -o lpi.iso .
$ mv lpi.iso /tmp/
# mount -t iso9660 /tmp/lpi.iso /mnt/
mount: /mnt: WARNING: device write-protected, mounted read-only.
# tree -L 1 /mnt/
/mnt/
 -- 101_syst
 - 102_linu
- 103_gnu_
  - 104 devi
  — data_sou
    _git
  - howto lp.pdf
  - question
  - readme.md
  - resource.md
  - workmap.md
# umount /mnt
```

The *loop* option to the mount command is used to mount special filesystems that are stored within a file. These files have the extension of .img or .iso

```
# 6
# mount -t ext4 -o loop linux.img /mnt
# umount /mnt
```

```
# mount -t iso9660 -o loop /tmp/lpi.iso /mnt/
mount: /mnt: WARNING: device write-protected, mounted read-only.
# umount /mnt
```

Manual Umount filesystems

- Filesystem can be detached, removed directly. First they had to be unmounted. Direct unplug removable devices may cause disk damage.
- Can't be unmounted if the active directory is in the device.
- Can't be unmounted if processes use the device.

```
#7
# mount -t ext4 linux.img /mnt
# cd /mnt/
# ls
lost+found message.txt
# umount /mnt
umount: /mnt: target is busy.
```

```
# lsof /mnt
lsof: WARNING: can't stat() fuse.gvfsd-fuse file system /run/user/1001/gvfs
        Output information may be incomplete.
lsof: WARNING: can't stat() fuse.portal file system /run/user/1001/doc
        Output information may be incomplete.
            PID USER FD TYPE DEVICE SIZE/OFF NODE NAME
COMMAND
                                                           1024

        bash
        16214 root
        cwd
        DIR

        lsof
        17419 root
        cwd
        DIR

        lsof
        17420 root
        cwd
        DIR

                                                7,2
                                                                       2 /mnt
                                                7,2
                                                           1024
                                                                       2 /mnt
                                                7,2
                                                           1024
                                                                       2 /mnt
```

```
#9
# fuser -v /mnt/
USER PID ACCESS COMMAND
/mnt: root kernel mount /mnt
root 16214 ..c.. bash
```

Fuser codes:

- c The process is using the mount point or a subdirectory as its current directory.
- e The process is an executable file that resides in the mount point structure.
- f The process has an open file from the mount point structure.
- F The proc has an open file from the mount point structure that it is writing to.
- r The process is using the mount point as the root directory.
- m The process is a mmap'ed file or shared library.

```
#10
# cd ..
# umount /mnt
```

Automatically mounting filesystems on boot: fstab

The /etc/fstab file is used to configure what filesystems will be mounted automatically at boot. It can also be used to activate swap devices automatically. Root privileges are required to make changes to the /etc/fstab file.

Device identifiers:

- device name
- device UUID
- device label

```
#11
# blkid
/dev/nvme0n1p1: SEC TYPE="msdos" UUID="7F70-2AC1" BLOCK SIZE="512" TYPE="vfat"
PARTLABEL="EFI System Partition" PARTUUID="e556663a-ed3f-4d5b-b69e-0abe9158c16b"
/dev/nvme0n1p2: UUID="027d32d8-de03-40d5-ad80-453618bd71a8" BLOCK SIZE="4096"
TYPE="ext4" PARTUUID="11ae4b81-2f10-4a68-a7cb-4c7fd2229678"
/dev/nvme0n1p3: UUID="VgZxLA-HigE-eyyU-DBHj-XbyP-e2gF-LEzdtR" TYPE="LVM2 member"
PARTUUID="d4560004-ae55-4c3c-adee-1729a188417e"
/dev/mapper/fedora-root: UUID="a00558ae-7865-4baa-b186-df0aaf2ab482" BLOCK SIZE="4096"
TYPE="ext4"
/dev/mapper/fedora-swap: UUID="6cc2a9b5-50dd-4786-b0da-8239c67ed9ee" TYPE="swap"
/dev/mapper/fedora-home: UUID="06206a20-a62a-498e-a8d8-cd126855b435" BLOCK SIZE="4096"
TYPE="ext4"
/dev/loop0p1: UUID="ff9408dc-9b60-417c-af70-9fc530986562" BLOCK SIZE="4096" TYPE="ext4"
/dev/loop1: BLOCK_SIZE="2048" UUID="2021-10-26-17-26-48-00" LABEL="CDROM" TYPE="iso9660"
# tree /dev/disk
```

```
#13
# mount xfs.img /mnt/

# xfs_admin -L mylabel /dev/loop0
label = "mylabel"

# blkid -t xfs
# umount /mnt
```

fstab

Filesystem tabulation file. Defines the filesystems to mount on startup.

```
device mountpoint fstype options dump check
```

Attributes:

- device. Identify the device. Can be device name, UUID or LABEL.
- *mountpoint*. Filesystem directory where to mount the device.
- fstype. identify the fstype. Can be auto to autodetect.
- options: options to apply to the filesystem. defaults, rw, ro, user, users, noauto...
- default options (and opposite):
 - rw Allow reading and writing. ro.
 - o suid Allow suid executes nosuid
 - o dev Allow device files nodev
 - o exec Allow executable files noexec
 - o auto Automatically mount noauto
 - nouser Prevent ordinary users from mounting or unmounting the partition.
 Using the user option allows non-root users to mount that particular device, which is helpful for removable media. user users
 - async All writes should be asynchronous sync
 - relatime Only update access time on file access if the file has been modified or its metadata changed since last access N/A
- *dump*. (obsolete) The purpose of this field is to tell an administrator which filesystems should be backed up when using the dump command.
- *check*. determe the order in which the filesystems will be checked by the fsck utility during system boot. 0 no check. 1 checks before 2, etc.

```
# cat /etc/fstab
 /etc/fstab
# Created by anaconda on Wed Apr 7 10:55:55 2021
# Accessible filesystems, by reference, are maintained under '/dev/disk'
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
/dev/mapper/fedora-root /
                                               ext4 defaults
UUID=027d32d8-de03-40d5-ad80-453618bd71a8 /boot
                                                                  defaults
                                                                                  1 2
                                                         ext4
                       /boot/efi
                                               vfat umask=0077,shortname=winnt 0 2
IIIIID=7F70-2AC1
/dev/mapper/fedora-home /home
                                               ext4
                                                    defaults
                                                                       1 2
/dev/mapper/fedora-swap swap
                                                                       0 0
                                                       defaults
```

When defined in /etc/fstab filesystems can be mounted and unmounted easily:

- only specify device or mountpoint (not necessary both).
- options defined in /etc/fstab are applicated
- user can not mount unless user or users options are specified.

```
#15

# cat /etc/fstab

/dev/mapper/fedora-root / ext4 defaults 1 1

UUID=027d32d8-de03-40d5-ad80-453618bd71a8 /boot ext4 defaults 1 2
```

```
UUID=7F70-2AC1
                        /boot/efi
                                                vfat
                                                         umask=0077,shortname=winnt 0 2
/dev/mapper/fedora-home /home
                                                 ext4
                                                         defaults
                                                                         1 2
/dev/mapper/fedora-swap swap
                                                 swap
                                                         defaults
                                                                         0 0
                                                         defaults,ro
/home/images/linux.img /mnt
                                                 ext4
# mount -a
# mount -t ext4
/dev/mapper/fedora-root on / type ext4 (rw,relatime,seclabel)
/dev/nvme0n1p2 on /boot type ext4 (rw,relatime,seclabel)
/dev/mapper/fedora-home on /home type ext4 (rw,relatime,seclabel)
/home/images/VM/linux.img on /mnt type ext4 (ro,relatime,seclabel)
# umount /mnt
```

Define swap in /etc/fstab

Usually the swap partitions are defined in the /etc/fstab file.

```
/device swap swap defaults 0 0
```

Systemd mount units

The systemd-mount utility is the mechanism that systemd uses to create and start a transient .mount file, destroy a transient .mount file, or to start an .automount unit of the filesystem.

Systemd converts all entries in fstab in systemd-mount units

Root can create systemd-mount units.

```
# 16
# locate .mount
# cat /usr/lib/systemd/system/proc-fs-nfsd.mount
[Unit]
Description=NFSD configuration filesystem
[Mount]
What=nfsd
Where=/proc/fs/nfsd
Type=nfsd
# cat /usr/lib/systemd/system/tmp.mount
  SPDX-License-Identifier: LGPL-2.1+
 This file is part of systemd.
  systemd is free software; you can redistribute it and/or modify it
  under the terms of the GNU Lesser General Public License as published by
  the Free Software Foundation; either version 2.1 of the License, or
  (at your option) any later version.
Description=Temporary Directory (/tmp)
Documentation=https://systemd.io/TEMPORARY DIRECTORIES
```

```
Documentation=man:file-hierarchy(7)
Documentation=https://www.freedesktop.org/wiki/Software/systemd/APIFileSystems
ConditionPathIsSymbolicLink=!/tmp
DefaultDependencies=no
Conflicts=umount.target
Before=local-fs.target umount.target
After=swap.target

[Mount]
What=tmpfs
Where=/tmp
Type=tmpfs
Options=mode=1777,strictatime,nosuid,nodev
```

Examples

```
# mount
# mount -a
# mount -t ext4
# mount -t tmpfs
```

```
# mount /dev/sdb1 /home/images
# mount -o loop data.img /mnt
# mount -o ro LABEL=DATA /opt/data
# mount -o sync UUID=027d32d8-de03-40d5-ad80-453618bd71a8 /var/log
```

```
# umount /dev/sdb1
# umount /mnt
# umount /dev/sda5 /mnt
```

```
# du -h
# du -h -text4
# lsof /mnt
# fuser -v /mnt
```

Example exercices

- 1. Create 4 raw images and format them as: ext4, vfat, xfs and swap
- 2. Assign each partition a label.
- 3. Create 3 directories in /mnt with the names: linux, windows, xfs.
- 4. mount the linux raw image to the linux directory read only.
- 5. mount the vfat partition to the windows directory using its label.
- 6. mount the xfs partition to the xfs directory using its UUID.
- 7. list all the mounted systems (mount and blkid).

- 8. umount all the raw images.
- 9. Modify the fstab file mounting the swap partiton automatically.
- 10. Modify the fstab file mounting the raw image linux to /mnt automatically.
- 11. Mount all the defined mounts in fstab. Verify it.
- 12. Comment the last two exercise entries in the fstab
- 13. LPI Exercices 104.3 Control mounting and unmounting of filesystems