

CentOS Linux

System Administrator's Guide

Storage Management

Prepared By: Emad Hussain

Table of Contents

SECTION I. Standard Partitioning in CentOS
1.1 Create new partition from a newly attached disk
1.2 Create another partition from an existing disk
1.3 Delete a partition from an existing disk
1.4 Extend existing partition without LVM using 'grow-part' utility
1.5 Extend existing partition without LVM using 'f-disk' utility
SECTION II. Linear LVM Partitioning in CentOS
2.1 Managing physical volumes (PV)
2.2 Managing volume groups (VG)
2.3 Managing logical volumes (LV)
Case I: Creating new LV(s) from scratch
Case II: Extend an existing LV(s) by increasing capacity of existing partition of drive (PV)
Case III: Extend an existing LV(s) by adding another drive to the machine
Case IV: Extend an existing LV(s) by reducing another LV of the same volume group
SECTION III. Stripped LVM Partitioning in CentOS
3.1 Creating a stripped LV
3.2 Extending a stripped LV
SECTION IV. Managing RAID 0 Array
3.1
3.2

1. Standard Partitioning

The standard partitioning scheme typically refers to the use of traditional disk partitioning methods, such as using the MBR (Master Boot Record) or GPT (GUID Partition Table) partitioning schemes. These schemes divide the disk into multiple partitions to organize and manage the storage space.

1.1 Below are the steps to create a new partition from a newly attached disk drive:

1. First, check the available disks on your machine using "lsblk" command.

```
[root@sysadmin ~]# lsblk
                  MAJ:MIN RM
                             SIZE RO TYPE MOUNTPOINT
NAME
sda
                    8:0
                          0
                              60G
                                   0 disk
                               1G 0 part /boot
—sda1
                    8:1
                          0
 -sda2
                    8:2 0 59G 0 part
                          0 38.3G 0 lvm
   -centos_vm-root 253:0
                                          [SWAP]
   -centos_vm-swap 253:1
   centos_vm-home 253:2
                          0 18.7G
                                   0 lvm
                                          /home
                   11:0
                           1 1024M
                                   0 rom
```

2. Listed below, actual hard-disk "sda" is partition into sda(1) & sda(2), the sda(2) is further divided into different LV(s) using LVM system. This the default LVM created by OS while installation.

- 3. Let's add the new hard-drive. I'm going to add 5 GB disk to my machine.
- 4. After adding new disk, list the available disk on your machine. The results will now show the newly added hard-drive.
- 5. If the new drive is not visible in available disks, you have to rescan all the "SCSI" hosts to make it visible.

echo "- - - " | tee /sys/class/scsi_host/host*/scan

```
[root@sysadmin ~]# echo "- - -" | tee /sys/class/scsi_host/host*/scan
[root@sysadmin ~]# lsblk
                  MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
sda
                    8:0
                              60G 0 disk
                               1G 0 part /boot
                              59G 0 part
  sda2
                          0 38.3G
   -centos_vm-root 253:0
   centos_vm-swap 253:1
                                           [SWAP]
    centos_vm-home 253:2
                           0 18.7G
                                   0 lvm
                    8:16
                                    0 disk
```

6. Alternatively, you can use the "rescan-scsi-bus.sh" script contained in "sg3_utils" package to scan all the hosts.

```
yum install sg3_utils rescan-scsi-bus.sh
```

7. By default, "fdisk" utility build the new drive using "DOS" partitioning scheme. Before proceeding with partitioning the disk, change the partition table of newly attached disk to "GPT".

```
[root@sysadmin ~]# fdisk /dev/sdb
Welcome to fdisk (util-linux 2.23.2).

Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table
Building a new DOS disklabel with disk identifier 0x8dd337b5.

Command (m for help): |
```

Press "g" to change the partition.

```
Command (m for help): g
Building a new GPT disklabel (GUID: 3052B452-8972-48B2-A130-EC008B9B2BF4)
```

Press "w" to save the changes.

```
Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table.

Syncing disks.

[root@sysadmin ~]# blkid /dev/sdb
/dev/sdb: PTTYPE="gpt"
```

8. Create a partition from a newly attached disk, in this case "sdb" using "fdisk" utility.

fdisk /dev/sdb

```
[root@sysadmin ~]# fdisk /dev/sdb
Welcome to fdisk (util-linux 2.23.2).

Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table
Building a new DOS disklabel with disk identifier 0x8dd337b5.

Command (m for help):
```

Press 'n' to add a new partition to the selected disk.

```
Command (m for help): n
Partition type:
   p primary (0 primary, 0 extended, 4 free)
   e extended
Select (default p):
```

Proceed with default 'p' option, now next select partition number (1-4), go ahead with default first sector value. Now, it prompts for the last sector value, the whole drive (5 GB) will be partitioned, if you don't specify the last sector size. In this case, I'm partitioning with only "2 GB" out of total "5 GB".

```
Command (m for help): n

Partition type:
    p primary (0 primary, 0 extended, 4 free)
    e extended

Select (default p): p

Partition number (1-4, default 1): 1

First sector (2048-10485759, default 2048):

Using default value 2048

Last sector, +sectors or +size{K,M,G} (2048-10485759, default 10485759): +2G

Partition 1 of type Linux and of size 2 GiB is set
```

Press "p" to print available partitions for the selected drive (sdb).

```
Command (m for help): p
Disk /dev/sdb: 5368 MB, 5368709120 bytes, 10485760 sectors Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x33762e31
   Device Boot
                       Start
                                      End
                                                Blocks
                                                           Id System
                                  4196351
/dev/sdb1
                        2048
                                               2097152
                                                           83 Linux
```

By default, the drive partitioned to a "Linux" filesystem type. However, there is still a need to format a partition to a filesystem type "ext4,xfs".

Press 'w' to save for the changes.

```
Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table.

Syncing disks.
```

9. Verify the the new created partition for "sdb" disk using "lsblk" command.

```
[root@sysadmin ~]# lsblk
NAME
                  MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
sda
                    8:0
                               60G 0 disk
                    8:1
                           0
                               1G 0 part /boot
 -sda1
 -sda2
                    8:2
                              59G
                                   0 part
                         0 38.3G
   -centos_vm-root 253:0
                                   0 lvm
   -centos_vm-swap 253:1
                                2G 0 lvm
                                           [SWAP]
  Centos_vm-home 253:2
                           0 18.7G
                                   0 lvm
                                          /home
sdb
                    8:16
                                5G
                                   0 disk
                           0
└─sdb1
                                2G 0 part
                    8:17
                           0
sr0
                   11:0
                          1 1024M 0 rom
```

10. Now format "sdb1" with the appropriate filesystem. I'm formatting with "xfs".

mkfs.xfs -L sysadmin_fs /dev/sdb1

```
[root@sysadmin ~]# mkfs.xfs -L sysadmin_fs /dev/sdb1
meta-data=/dev/sdb1
                                     isize=512
                                                   agcount=4, agsize=131072 blks
                                     sectsz=512 attr=2, projid32bit=1
                                    crc=1 finobt=0, sparse=0
bsize=4096 blocks=524288, imaxpct=25
data
                                     sunit=0
                                                   swidth=0 blks
                                    bsize=4096
naming
         =version 2
                                                   ascii-ci=0 ftype=1
                                     bsize=4096
                                                   blocks=2560, version=2
sunit=0 blks, lazy-count=1
         =internal log
                                     sectsz=512
realtime =none
                                     extsz=4096
                                                   blocks=0, rtextents=0
```

11. Validate the formatted FS using "blkid" command.

blkid /dev/sdb1

```
[root@sysadmin ~]# blkid /dev/sdb1
/dev/sdb1: LABEL="sysadmin_fs" UUID="72c64ae8-b7bf-4b97-9a8d-6728e6ff3969" TYPE="xfs"
PARTUUID="7cd853af-6b68-4b80-87c3-ca591804756c"
```

- 12. Let's mount "sdb1" to a specific mount location.
- 13. You can mount partition on any location, here I'm going to create a custom directory and mount the partition on that custom mount point.

```
mkdir -p /sysadmin_mountpoint
mount /dev/sdb1 /sysadmin_mountpoint
```

```
[root@sysadmin ~]# mkdir -p /sysadmin_mountpoint
[root@sysadmin ~]# mount /dev/sdb1 /sysadmin_mountpoint
```

14. Verify the mount using "df -h" command.

```
root@sysadmin ~]# df -h
ilesystem
                            Size Used Avail Use% Mounted on
devtmpfs
                             475M
                                         475M
                                      0
tmpfs
                                                0% /dev/shm
                            487M
                                         487M
tmpfs
                            487M
                                  7.7M
                                         479M
                                                 2% /run
                                                0% /sys/fs/cgroup
                                         487M
                            487M
cmpfs
                                     0
dev/mapper/centos_vm-root
                             39G
                                   1.6G
                             19G
                                                 1% /home
dev/mapper/centos_vm-home
                                    33M
dev/sda1
                            1014M
                                   169M
                                         846M
                                                17% /boot
                             98M
                                          98M
                                                0% /run/user/0
mpfs
                                      0
dev/sdb1
                            2.0G
                                    33M
                                         2.0G
                                                    /sysadmin_mountpoint
```

- 15. To automatically mount the above the partition or drive on the specific mount location, we have to make configuration changes to the "/etc/fstab" file. The "fstab" file in Linux is used to define and configure the filesystems (partitions) that are automatically mounted during the system boot process.
- 16. Let's edit the file using "vi/nano" editor and the add following line.

/sysadmin_mountpoint

vi /etc/fstab /dev/sdb1

xfs defaults UUID=02738ca7-6b46-4fb2-b4c3-093352dd8b6f /boot xfs defaults 0 0 /dev/mapper/centos_vm-home /home xfs defaults 0 0 /dev/mapper/centos_vm-swap swap defaults 0 0 swap xfs /dev/sdb1 /sysadmin_mountpoint defaults

defaults

1

2

xfs

"/dev/sdb1": This is the device or partition that will be mounted. In this case, it refers to the device file /dev/sdb1.

"/sysadmin_mountpoint": This is the mount point, which is the directory where the filesystem will be attached. In this example, the filesystem will be mounted at the directory /sysadmin mountpoint.

"xfs": This specifies the filesystem type. In this case, it is XFS, which is a high-performance filesystem commonly used in Linux.

"defaults": This field specifies the mount options for the filesystem. The "defaults" option implies a standard set of mount options, including allowing read and write access, enabling atime (access time) updates, and using default file permissions.

"1": This field determines whether the filesystem should be backed up by the dump utility. A value of 1 indicates that the filesystem will be backed up.

"2": This field specifies the order in which filesystems are checked during the boot process by the fsck (filesystem check) utility. A value of 2 means that the filesystem will be checked after the root filesystem but before other filesystems with a value of 0.

Note: It's a best practice to always specify a filesystem in the "fstab" with their "UUIDs" because "/dev/sdb1" for example can change to "/dev/sdc1" after a system reboot which the "fstab" file will not be able to read the supposed populated filesystem.

1.2 Below are the steps to create another partition from existing drive using "parted" utility:

First, check the available disks and partitions on your machine using "lsblk" command.

```
[root@sysadmin ~]# lsblk
NAME
                 MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
sda
                   8:0
                         0
                             60G 0 disk
                   8:1
                             1G 0 part /boot
 -sda1
                         0
 -sda2
                   8:2
                       0 59G 0 part
  -centos_vm-root 253:0
                       0 38.3G 0 lvm
  -centos_vm-swap 253:1
                       Θ
                              2G 0 lvm [SWAP]
  _centos_vm-home 253:2
                        0 18.7G 0 lvm /home
sdb
                   8:16
                       0 15G 0 disk
∟sdb1
                   8:17
                         0
                             12G 0 part
sr0
                  11:0
                         1 1024M 0 rom
```

- 2. Above shown, you can see the drive "sdb" has (15 GB) total space, and a partition of (12 GB) is already created. We're now going to create another partition of available (3 GB) space.
- 3. Let's create another partition using "parted".

parted /dev/sdb

```
[root@sysadmin ~]# parted /dev/sdb
GNU Parted 3.1
Using /dev/sdb
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) |
```

Type 'print' to print the available partitions for drive "sdb".

```
(parted) print
Model: VMware, VMware Virtual S (scsi)
Disk /dev/sdb: 16.1GB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:
Number Start End Size File system Name Flags
1 1049kB 12.9GB 12.9GB ext4
```

Proceed for creating a new partition. Type 'mkpart' to create a new partition.

```
Command (m for help): n
Partition type:
   p primary (0 primary, 0 extended, 4 free)
   e extended
Select (default p):
```

Proceed with naming the new partition, you can leave it blank as well, next provide file system type, I'm opting for "ext4". Provide the start & end sector values for creating a partition.

```
(parted) mkpart
Partition name? []?
File system type? [ext2]? ext4
Start? 12.9GB
End? 16.1GB
```

Type 'print' to make sure that partitioning has been done for drive "sdb".

```
(parted) print
Model: VMware, VMware Virtual S (scsi)
Disk /dev/sdb: 16.1GB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:
Number Start End Size File system Name Flags
1 1049kB 12.9GB 12.9GB ext4
2 12.9GB 16.1GB 3221MB
```

Type 'quit' to exit from parted utility.

4. Confirm using "Isblk" command.

```
[root@sysadmin ~]# lsblk
                   MAJ:MIN RM
                               SIZE RO TYPE MOUNTPOINT
NAME
sda
                     8:0
                            0
                                60G 0 disk
                            0
 —sda1
                     8:1
                                 1G 0 part /boot
 -sda2
                     8:2
                                59G
                                     0 part
  -centos_vm-root 253:0
                          0 38.3G
                                     0 lvm
                                             [SWAP]
   -centos_vm-swap 253:1
                           0
                                     0 lvm
                                     0 lvm
  └─centos_vm-home 253:2
                            0 18.7G
sdb
                     8:16
                            0
                                15G
                                     0 disk
 -sdb1
                     8:17
                            0
                                 12G
                                     0 part
 -sdb2
                     8:18
                            0
                                 3G
                                     0 part
sr0
                    11:0
                            1 1024M
                                     0 rom
```

5. Now format "sdb2" with the appropriate filesystem. I'm formatting with "ext4".

mkfs.ext4 -L sysadmin_fs /dev/sdb2

6. Verify using "blkid" command

blkid /dev/sdb2

```
[root@sysadmin ~]# blkid /dev/sdb2 /dev/sdb2: LABEL="sysadmin_fs2" UUID="f793dd40-0892-4aae-9e7c-bc93484006bb" TYPE="ext4" PARTUUID="99747e8a-23cc-4453-863c-039cdcb1bd42"
```

- 7. Let's mount "sdb2" to a specific mount location.
- 8. You can mount partition on any location, here I'm going to create a custom directory and mount the partition on that custom mount point.

mkdir -p /sysadmin_mountpoint2 mount /dev/sdb1 /sysadmin_mountpoint

9. Verify the mount using "df -h" command.

```
[root@sysadmin ~]# df -h
Filesystem
                                   Used Avail Use% Mounted on
                             Size
devtmpfs
                             475M
                                      0 475M
                                                0% /dev
tmpfs
                                                0% /dev/shm
                             487M
                                         487M
tmpfs
                             487M
                                         479M
                                                 2% /run
tmpfs
                             487M
                                                0% /sys/fs/cgroup
                                         487M
                                      0
                                   2.3G
                                                6% /
/dev/mapper/centos_vm-root
                                          36G
                                                1% /home
/dev/mapper/centos_vm-home
                              19G
                                          19G
/dev/sda1
                            1014M
                                   169M
                                         846M
                                                17% /boot
tmpfs
                              98M
                                          98M
                                                0% /run/user/0
                                     0
/dev/sdb1
                              12G
                                          12G
                                                1% /sysadmin_mountpoint
/dev/sdb2
                             2.9G
                                   9.0M
                                         2.8G
                                                1% /sysadmin_mountpoint2
```

10. To automatically mount the above the partition or drive on the specific mount location. You can follow the above steps to make entry in "fstab" file.

1.3 Below are the steps to delete partition from existing drive using "parted" utility:

First, check the available disks and partitions on your machine using "lsblk" command.

```
[root@sysadmin ~]# lsblk
NAME
                   MAJ:MIN RM
                               SIZE RO TYPE MOUNTPOINT
sda
                     8:0
                            0
                                60G
                                     0 disk
 -sda1
                     8:1
                            0
                                  1G
                                     0 part /boot
                                59G
 -sda2
                     8:2
                            0
                                     0 part
  -centos_vm-root 253:0
                            0 38.3G
                                     0
                                        lvm
   -centos_vm-swap 253:1
                            0
                                  2G
                                     0
                                        lvm
                                             [SWAP]
  _centos_vm-home 253:2
                            0 18.7G
                                     0
                                        lvm
                                             /home
sdb
                     8:16
                                15G
                            0
                                     0 disk
 -sdb1
                     8:17
                                12G
                                     0 part
  sdb2
                     8:18
                            0
                                  3G
                                     0 part
                            1 1024M
                    11:0
                                     0 rom
```

- 2. Above shown, you can see the drive "sdb" has two partitions sdb(1),sdb(2). I'm going to delete sdb(2) using parted.
- 3. Please be careful while deleting the partitions as , this process can make your machine(s) corrupt.
- 4. Un-mount the partition before deleting it.

umount /dev/sdb2

Let's delete partition sdb(2) using "parted".

parted /dev/sdb

```
[root@sysadmin ~]# parted /dev/sdb
GNU Parted 3.1
Using /dev/sdb
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) |
```

Type 'print' to print the available partitions for drive "sdb".

```
(parted) print
Model: VMware, VMware Virtual S (scsi)
Disk /dev/sdb: 16.1GB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:

Number Start End Size File system Name Flags
1 1049kB 12.9GB 12.9GB ext4
2 12.9GB 16.1GB 3221MB ext4
```

Proceed for deleting partition sdb(2). Type 'rm <partition-number>' to delete a new partition.

```
(parted) rm 2
(parted) |
```

Type 'print' to print the available partitions for drive "sdb".

```
(parted) print
Model: VMware, VMware Virtual S (scsi)
Disk /dev/sdb: 16.1GB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:

Number Start End Size File system Name Flags
1 1049kB 12.9GB 12.9GB ext4
```

Type 'quit' to exit from parted utility.

6. Confirm using "lsblk" command.

```
[root@sysadmin ~]# lsblk
NAME MAJ.M
                   MAJ:MIN RM
                               SIZE RO TYPE MOUNTPOINT
                                60G 0 disk
sda
                                1G 0 part /boot
 -sda1
                                59G 0 part
—sda2
                            0 38.3G 0 lvm
   -centos_vm-root 253:0
                                            [SWAP]
   -centos_vm-swap 253:1
  centos_vm-home 253:2
                            0 18.7G 0 lvm
                                            /home
sdb
Lsdb1
                                     0 part /sysadmin_mountpoint
                            1 1024M
                                     0 rom
```

7. You can see above, partition sdb(2) has been removed.

Note: Make sure to take backup before removing any partition. It is recommended to always perform this action using "parted utility" as this can be somewhat safer compared to other tools. Other tools, can make your OS stuck at next boot after deleting a partition.

1.4 Below are the steps to extend an existing partition without LVM using "growpart" utility: (Recommended)

1. First, check the available disks and partitions on your machine using "Isblk" command.

```
[root@sysadmin ~]# lsblk
                  MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
NAME
sda
                              60G 0 disk
-sda1
                    8:1
                               1G 0 part /boot
                             59G 0 part
—sda2
                         0 38.3G 0 lvm
                                           [SWAP]
   centos_vm-swap 253:1
  _centos_vm-home 253:2
                          0 18.7G
                                   0 lvm
                                          /home
sdb
                   8:16 0
                                   0 disk
∟sdb1
                                   0 part /sysadmin_mountpoint
                           1 1024M
sr0
                   11:0
                                   0 rom
```

- 2. Now increase the size of your drive from backend, and rescan the SCSI hosts using the steps given above. Here I've already done these steps, we have "sdb" drive of total size (10 GB). I'm going to increase the size of partition "sdb1" from (5 GB) to (10 GB) using growpart utility.
- 3. First make sure the growpart-utils are installed on your machine.

yum install cloud-utils-growpart gdisk

4. Let's increase the size of "sdb1" to (10 GB).

growpart /dev/sdb 1

```
[root@sysadmin ~]# growpart /dev/sdb 1
CHANGED: partition=1 start=2048 old: size=10485760 end=10487808 new: size=20967424 end=20969472
```

5. You need to use the "resize2fs or xfs_growfs" command to resize the filesystem after extending a partition to ensure that the filesystem recognizes and utilizes the additional space. Since in this case, partition "sdb1" FS was "xfs" so I use "xfs_growfs" for resizing. For ext(s) file systems, use "resize2fs"

xfs growfs /dev/sdb1

```
[root@sysadmin ~]# xfs_growfs /dev/sdb1
meta-data=/dev/sdb1
                                              agcount=4, agsize=327680 blks
                                 isize=512
                                 sectsz=512
                                              attr=2, projid32bit=1
                                              finobt=0 spinodes=0
                                 crc=1
data
                                 bsize=4096
                                              blocks=1310720, imaxpct=25
                                 sunit=0
                                              swidth=0 blks
                                 bsize=4096
naming
         =version 2
                                              ascii-ci=0 ftype=1
         =internal
                                 bsize=4096
                                              blocks=2560, version=2
log
                                              sunit=0 blks, lazy-count=1
                                 sectsz=512
realtime =none
                                 extsz=4096
                                              blocks=0, rtextents=0
data blocks changed from 1310720 to 2620928
```

6. Verify using "df -h" command.

```
[root@sysadmin ~]# df -h
                                   Used Avail Use% Mounted on
Filesystem
                             Size
                             475M
                                        475M
devtmpfs
                                      0
                                                0% /dev
tmpfs
                             487M
                                         487M
                                                0% /dev/shm
                                   7.7M
                             487M
                                         479M
                                                2% /run
                             487M
                                         487M
                                                0% /sys/fs/cgroup
                                      0
/dev/mapper/centos_vm-root
                              39G
                                   2.3G
                                          36G
                                                6% /
                                                1% /home
/dev/mapper/centos_vm-home
                              19G
                                    33M
                                          19G
                                         846M
/dev/sda1
                            1014M
                                   169M
                                               17% /boot
                              98M
                                          98M
tmpfs
                                     0
                                                0% /run/user/0
/dev/sdb1
                              10G
                                  773M 9.3G
                                                8% /sysadmin_mountpoint
```

1.5 Below are the steps to extend an existing partition without LVM using fdisk utility:

1. First, check the available disks and partitions on your machine using "lsblk" command.

```
[root@sysadmin ~]# lsblk
                  MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
NAME
sda
                                60G 0 disk
                     8:1
                                    0 part /boot
 -sda1
                    8:2
                                59G
                                    0 part
 -sda2
   -centos_vm-root 253:0
                           0 38.3G 0 lvm
                                 2G 0 lvm
                                            [SWAP]
   -centos_vm-swap 253:1
   centos_vm-home 253:2
                           0 18.7G
                                    0 lvm
                                            /home
                                    0 disk
                    8:16
                           0
                                 5G
Lsdb1
                                 2G 0 part /sysadmin_mountpoint
                    8:17
                            1 1024M 0 rom
                    11:0
sr0
```

2. Here we have "sdb" drive of total size (5 GB).

```
[root@sysadmin ~]# lsblk
NAME
                   MAJ:MIN RM
                               SIZE RO TYPE MOUNTPOINT
                                60G 0 disk
                     8:0
sda
 —sda1
                     8:1
                                     0 part /boot
 -sda2
                     8:2
                                59G
                                     0 part
   -centos_vm-root 253:0
                            0 38.3G
    -centos_vm-swap 253:1
                                            [SWAP]
                            0 18.7G
                   253:2
                                     0 lvm
    -centos_vm-home
sdb
                     8:16 0
                                 5G 0 disk
                                     0 part /sysadmin_mountpoint
                              1024M
```

- 3. I'm going to enhance the hard drive size of my machine from backend. To do this, maybe you have to power off your machine.
- 4. You can see the drive size has been increased from (5 GB) to (10 GB).

```
MAJ:MIN RM
                               SIZE RO TYPE MOUNTPOINT
                     8:0
                            0
                                     0 disk
sda
                     8:1
–sda1
 -sda2
                     8:2
                                     0 part
  -centos_vm-root 253:0
                            0 38.3G
                                             [SWAP]
   -centos_vm-swap
   centos_vm-home
                                      0 lvm
                    8:16
                                10G 0 disk
                                      0 part /sysadmin_mountpoint
                              1024M
```

You can also see the consumed space for sdb1.

6. Un-mount the partition

umount /sysadmin_mountpoint

```
[root@sysadmin /]# umount /sysadmin_mountpoint
[root@sysadmin /]# df -h
                            Size Used Avail Use% Mounted on
Filesystem
devtmpfs
                                     0 475M
tmpfs
                                        487M
                                                0% /dev/shm
tmpfs
                                                2% /run
                                  7.6M
                            487M
                                        479M
                                                0% /sys/fs/cgroup
tmpfs
                            487M
                                        487M
/dev/mapper/centos_vm-root
                                  1.8G
                                                5%
                                                1% /home
/dev/mapper/centos_vm-home
                                   33M
                                               17% /boot
/dev/sda1
                           1014M
                                  169M
                                        846M
```

- 7. Make sure to backup the data before extending a standard partition.
- 8. Extend the partition "sdb1" of disk "sdb" using "fdisk" utility.

fdisk /dev/sdb

```
[root@sysadmin ~]# fdisk /dev/sdb
Welcome to fdisk (util-linux 2.23.2).
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.
```

Press 'p' to print the available partitions for drive "sdb".

```
Command (m for help): p
Disk /dev/sdb: 10.7 GB, 10737418240 bytes, 20971520 sectors Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x00000000
   Device Boot
                                    End
                                               Blocks
                      Start
                                                        Id System
                               10485759
/dev/sdb1
                                              5242879+ ee
                                                             GPT
Command (m for help):
```

Press 'd' to delete the partition, if multiple partitions available, identify the partition number and then specify it while deleting.

```
Command (m for help): d
Selected partition 1
Partition 1 is deleted
Command (m for help):
```

Proceed for creating a new partition with new allocated space. Press 'n' to create a new partition.

```
Command (m for help): n
Partition type:
   p primary (0 primary, 0 extended, 4 free)
   e extended
Select (default p): |
```

Proceed with default 'p' option, now next select partition number (1-4), go ahead with default first sector value. Now, it prompts for the last sector value, the whole drive (10 GB) will be partitioned, if you don't specify the last sector size. In this case, I'm partitioning with only "7 GB" out of total "10 GB" available.

```
Command (m for help): n

Partition type:
    p   primary (0 primary, 0 extended, 4 free)
    e   extended

Select (default p):
Using default response p

Partition number (1-4, default 1): 1

First sector (2048-20971519, default 2048):
Using default value 2048

Last sector, +sectors or +size{K,M,G} (2048-20971519, default 20971519): +7G

Partition 1 of type Linux and of size 7 GiB is set
```

Press 'w' to save the changes made to disk.

```
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
```

9. Now mount the extended partition on the same mount point.

mount /dev/sdb1 /sysadmin_mountpoint

10. You need to use the "resize2fs or xfs_growfs" command to resize the filesystem after extending a partition to ensure that the filesystem recognizes and utilizes the additional space. Since in this case, partition "sdb1" FS was "xfs" so I use "xfs_growfs" for resizing. For ext(s) file systems, use "resize2fs"

xfs_growfs /dev/sdb1

```
meta-data=/dev/sdb1
                                                 agcount=4, agsize=131072 blks
                                   isize=512
                                   sectsz=512
                                                 attr=2, projid32bit=1
                                                 finobt=0 spinodes=0
                                   bsize=4096
data
                                                 blocks=524288, imaxpct=25
                                                 swidth=0 blks
                                   sunit=0
                                   bsize=4096
naming
         =version 2
                                                 ascii-ci=0 ftype=1
                                                 blocks=2560, version=2
sunit=0 blks, lazy-count=1
                                   bsize=4096
log
                                   extsz=4096
realtime =none
                                                 blocks=0, rtextents=0
data blocks changed from 524288 to 1835008
```

11. Verify the extended space using the "df -h" command.

```
[root@sysadmin ~]# df -h
Filesystem
                            Size Used Avail Use% Mounted on
devtmpfs
                            475M
                                     0 475M
                                               0% /dev
tmpfs
                            487M
                                     0 487M
                                               0% /dev/shm
tmpfs
                                  7.7M
                            487M
                                        479M
                            487M
                                        487M
                                               0% /sys/fs/cgroup
/dev/mapper/centos_vm-root
                                  1.8G
                                               5% /
/dev/mapper/centos_vm-home
                                         19G
/dev/sda1
                           1014M
                                  169M
                                        846M
                                              17% /boot
tmpfs
                             98M
                                         98M
                                               0% /run/user/0
                                     0
/dev/sdb1
                            7.0G
                                        6.3G
                                              11% /sysadmin_mountpoint
```


12. Above, it is noticed that the "sdb(1)" space has been extended from (5 GB) to (10 GB).

2. Linear LVM Partitioning

LVM stands for Logical Volume Management. This is an alternative method of managing storage systems than the traditional partition-based one. In LVM, instead of creating partitions, you create logical volumes, and then you can just as easily mount those volumes in your filesystem as you'd a disk partition. The main advantage of LVM is how easy it is to resize a logical volume or volume group. It abstracts away all the ugly parts (partitions, raw disks) and leaves us with a central storage pool to work with.

There are three main components to LVM:

- 1. Physical Volumes
- 2. Volume Groups
- 3. Logical Volumes
- 4. Physical Extents
- 5. Logical Extents





Physical Volumes:

Physical volumes are the raw materials or building blocks that are used to achieve the abstraction that is logical volumes. In simpler words, physical volumes are the logical unit of an LVM system. Physical volume(s) are created from block devices. A block device could be LUNS created from the storage array, the physical hard drive or even a partition on a disk. Creating and initializing a physical volume are the same thing. Both mean you're just preparing the building blocks (i.e., partitions, disks) for further operations.

Volume Groups:

Volume groups are collections of physical volumes. It is the next level of abstraction in LVM. Volume groups are the storage pool that combines the storage capacity of multiple raw storage devices.

Logical Groups:

A logical volume is like a partition, but instead of sitting on top of a raw disk, it sits on top of a volume group. You can format a logical volume with whichever filesystem you want. Mount it anywhere in the filesystem you want.

Physical Extents:

Physical extent represents a fixed-size block of storage in LVM. It refers to a contiguous portion of a physical disk or a RAID array that is allocated for use by LVM. The size of a physical extent is determined during the creation of a Volume Group (VG) in LVM. All physical extents within a Volume Group have the same size, and this size is typically set to a power of two, such as 4MB or 8MB.

When you create logical volumes (LVs) within a Volume Group, they are divided into smaller units called logical extents, which are mapped to physical extents on the underlying physical storage devices.

Logical Extents:

A logical extent represents a portion of a logical volume (LV) in LVM. It is an abstraction that allows LVM to manage the allocation and mapping of logical volumes to physical extents. The size of a logical extent is the same as the size of a physical extent in the associated Volume Group.

Logical extents are grouped together to form logical volumes, which can be formatted with a file system and mounted as a regular storage device within the operating system. The logical extents of a logical volume do not have to be contiguous on the physical storage; they can be spread across multiple physical devices, allowing for flexibility and management of storage resources.

2.1 Managing Physical Volumes (PV):

1. First, check the available disks on your machine using "lsblk" command.

```
[root@sysadmin ~]# lsblk
                   MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
NAME
                     8:0
                                60G 0 disk
sda
                     8:1
                            0
                                 1G 0 part /boot
 -sda1
 -sda2
                     8:2
                            0
                                59G 0 part
   —centos_vm-root 253:0
                            0 38.3G
                                     0 lvm
   -centos_vm-swap 253:1
                            0
                                 2G
                                     0 lvm
                                             [SWAP]
   -centos_vm-home 253:2
                            0 18.7G
                                     0
sdb
                     8:16
                            0
                                15G
                                     0 disk
                                20G
sdc
                     8:32
                                     0 disk
                            1 1024M 0 rom
sr0
                    11:0
```

2. Here, we have two physical drives "sdb" and "sdc" available right now. For now, we are going to create one PV from "sdb" drive.

pvcreate /dev/sdb

```
[root@sysadmin ~]# pvcreate /dev/sdb
Physical volume "/dev/sdb" successfully created.
[root@sysadmin ~]# |
```

3. You can verify created PV using "pvs" command.

4. Now we'll be partition "sdc" into sdc(1) & sdc(2). You can use above steps to create a partition using fdisk or any other tool.

```
[root@sysadmin ~]# lsblk
NAME
                   MAJ:MIN RM
                                SIZE RO TYPE MOUNTPOINT
                                60G 0 disk
sda
                     8:0
                            0
 -sda1
                     8:1
                                 1G 0 part /boot
  -sda2
                                 59G
                                      0 part
                                      0 lvm
                            0 38.3G
    -centos_vm-swap 253:1
                                             [SWAP]
   -centos_vm-home 253:2
                            0 18.7G
                                     0 lvm
sdb
                     8:16
                                      0 disk
sdc
                                 20G
                                      0 disk
                                     0 part
                     8:33
                                 10G
  -sdc1
                                      0 part
                     11 . 0
                               102UM
```

- 5. Here above we have created sdc(1) of (10 GB) & sdc(2) of (5 GB) out of total (20 GB) space available.
- 6. Create two PV(s) from these newly created partitions.

pvcreate /dev/sdc1 /dev/sdc2

```
[root@sysadmin ~]# pvcreate /dev/sdc1 /dev/sdc2
  Physical volume "/dev/sdc1" successfully created.
  Physical volume "/dev/sdc2" successfully created.
```

7. You can verify available physical volumes using "pvs" command.

8. You can also remove a PV using "pvremove" command.

```
[root@sysadmin ~]# pvremove /dev/sdc2
Labels on physical volume "/dev/sdc2" successfully wiped.
```

9. You can verify available physical volumes using "pvs" command.

```
[root@sysadmin ~]# pvs
PV VG Fmt Attr PSize PFree
/dev/sda2 centos_vm lvm2 a-- <59.00g 4.00m
/dev/sdb lvm2 --- 15.00g 15.00g
/dev/sdc1 lvm2 --- 10.00g 10.00g
```

10. Here, you can see sdc(2) has been removed.

2.2 Managing Volume Groups (VG):

1. Let's create a volume group from two PV(s) (sdb,sdc1)

```
vgcreate <vg-name> <pv-1> <pv-2>
```

```
[root@sysadmin ~]# vgcreate sysadmin_VG_1 /dev/sdb /dev/sdc1
Volume group "sysadmin_VG_1" successfully created
```

2. You can list all the volume groups using "vgs" command.

3. You can also extend the existing volume group with a new PV. I'm adding "sdc(2)" to our existing volume group we just created "sysadmin_VG_1"

```
vgextend <vg-name> <pv-1> <pv-2>
```

```
[root@sysadmin ~]# vgextend sysadmin_VG_1 /dev/sdc2
Volume group "sysadmin_VG_1" successfully extended
```

4. List all the volume groups to verify extended VG, using "vgs" command.

- 5. Here above, you can see volume group "sysadmin_VG_1" has been extended successfully.
- 6. You can also reduce a volume group using "vgreduce" command

```
vgreduce <vg-name> <pv-1> <pv-2>
```

```
[root@sysadmin ~]# vgreduce sysadmin_VG_1 /dev/sdc2
Removed "/dev/sdc2" from volume group "sysadmin_VG_1"
```

7. List all the volume groups to verify reduced VG, using "vgs" command.

```
[root@sysadmin ~]# vgs
VG #PV #LV #SN Attr VSize VFree
centos_vm 1 3 0 wz--n- <59.00g 4.00m
sysadmin_VG_1 2 0 0 wz--n- 24.99g 24.99g
```

8. The whole volume group can be removed using "vgremove" command vgremove <vg-name>

2.3 Managing Logical Volumes (LV):

Case I: Creating new LV from Scratch

 Let's create a logical volume from VG. I'm creating LV of size 8 GB on our VG "sysadmin_VG_1" lvcreate -L <size> -n <lv-name> <vg-name>

```
[root@sysadmin ~]# lvcreate -L 8GB -n sysadmin_LV_1 sysadmin_VG_1
Logical volume "sysadmin_LV_1" created.
```

2. You can list all the volume groups using "vgs" command.

```
VG #PV #LV #SN Attr VSize VFree
centos_vm 1 3 0 wz--n- <59.00g 4.00m
sysadmin_VG_1 2 1 0 wz--n- 24.99g 16.99g
```

3. Verify the created LV using "lvs" command.

```
[root@sysadmin ~]# lvs

LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert

home centos_vm -wi-ao---- <18.70g

root centos_vm -wi-ao---- <38.30g

swap centos_vm -wi-ao---- 2.00g

sysadmin_LV_1 sysadmin_VG_1 -wi-a---- 8.00g
```

4. Format the newly created LVM.

mkfs.ext4 /dev/<vg-name>/<lv-name>

5. You can verify FS type using "blkid" command

```
[root@sysadmin ~]# blkid /dev/sysadmin_VG_1/sysadmin_LV_1
/dev/sysadmin_VG_1/sysadmin_LV_1: UUID="03d3c368-054d-4356-a68a-790eb4d05f24" TYPE="ext4"
```

6. Mount the LV on the any location

mount <lv-name> <mount-location>

7. Verify using "df -h" command

```
[root@sysadmin ~]# df -h
Filesystem
                                            Size
                                                  Used Avail Use% Mounted on
                                                        475M
devtmpfs
                                                                0% /dev
tmpfs
                                            487M
                                                     0
                                                        487M
                                                                0% /dev/shm
tmpfs
                                            487M
                                                  7.7M
                                                        479M
                                                                2% /run
                                            487M
                                                     0
                                                        487M
tmofs
/dev/mapper/centos_vm-root
                                             39G
                                                  1.6G
                                                         37G
                                                                5% /
                                                               17% /boot
/dev/sda1
                                           1014M
                                                  169M
                                                         846M
/dev/mapper/centos_vm-home
                                                   33M
                                                         19G
                                                                1% /home
                                             98M
                                                          98M
                                                                0% /run/user/0
                                                     0
                                           7.8G
                                                        7.3G
/dev/mapper/sysadmin_VG_1-sysadmin_LV_1
                                                   36M
                                                                1% /sysadmin_mountpoint
```

Case II: Extend an existing LV by increasing capacity of an existing partition of a drive (PV):

1. First verify the LV that needs to be extended is part of which volume group using "lvs".

```
[root@sysadmin ~]# lvs
LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
home centos_vm -wi-ao---- <18.70g
root centos_vm -wi-ao---- <38.30g
swap centos_vm -wi-ao---- 2.00g
sysadmin_LV_1 sysadmin_VG_1 -wi-ao---- 24.99g
```

- I want to increase the space of "sysadmin_LV_1" which is a part of volume group "sysadmin VG 1".
- Let's check, if "sysadmin_VG_1" volume group has free space available using "vgs" & "pvs" command.

```
[root@svsadmin ~]# vgs
                                     VSize
  VG
                 #PV #LV #SN Attr
                                              VFree
                           0 \text{ wz}--n- < 59.00q 4.00m
 sysadmin_VG_1
                                      24.99a
[root@svsadmin ~]# pvs
                                 Attr PSize
                            Fmt
                                               PFree
  /dev/sda2 centos_vm
                           lvm2 a-- <59.00g 4.00m
             sysadmin_VG_1 lvm2 a--
                                      <15.00g
  /dev/sdc1 sysadmin_VG_1 lvm2 a-- <10.00g
  /dev/sdc2
                            lvm2 ---
                                        5.00g 5.00g
```

- 4. Here above you can see that our VG has no space left. We have to increase the space of any PV (drive/partition) that is a part of our VG. Above "sdb" or "sdc1" both are part of our VG "sysadmin_VG_1". I'm extending the space of "sdc" from backend.
- 5. I have increased the space of "sdc" from (20 GB) to (30 GB). Let's verify using "Isblk" command.

```
[root@sysadmin ~]# lsblk
NAME
                                  MAJ:MIN RM
                                              SIZE RO TYPE MOUNTPOINT
                                               60G
                                                    0 disk
sda
                                   8:0
                                           0
                                   8:1
                                           0
                                                1G
                                                    0 part /boot
 -sda1
                                               59G
  -sda2
                                   8:2
                                                    0 part
                                  253:0
                                             38.3G
   -centos_vm-root
                                                            [SWAP]
   -centos_vm-swap
                                  253:1
                                           0
                                                    0 lvm
                                  253:3
                                           0 18.7G
                                                            /home
   -centos_vm-home
                                   8:16
                                           0
                                               15G
                                                    0 disk
sdb
  -sysadmin_VG_1-sysadmin_LV_1
                                                    0 lvm
                                  253:2
                                                25G
                                   8:32
                                               40G
                                                    0 disk
                                               10G
                                                    0 part
  Lsysadmin_VG_1-sysadmin_LV_1 253:2
                                               25G
                                                    0 lvm
                                                    0 part
 -sdc2
                                   8:34
                                               20G
                                             1024M
```

If the changes is not reflect, follow the step 5 of SECTION 1.1, to rescan all the SCSI hosts.

6. Since partition "sdc(1)" is part of Volume Group "sysadmin_VG_1". So, we have to extend this partition first to make the free space available to VG. I'm using "grow-part" utility for this purpose.

growpart /dev/sdc 1

```
[root@sysadmin ~]# growpart /dev/sdc 1
NOCHANGE: partition 1 is size 20971520. it cannot be grown
```

7. Above listed error, I'm unable to increase the size sdc(1) even though I've increased my drive (sdc) space. This is because, the unallocated space resides at the end of drive. In our case right after partition "sdc(2)". To increase "sdc1" (PV) we have to delete "sdc2" to make the unallocated space available right after "sdc1" or we can attach a new disk drive and create PV from it, make that PV a part of our VG "sysadmin_VG_1". This whole picture is better illustrated below:

```
/dev/sda1
3.78 GiB unallocated
1.86 GiB
```

8. In this case, since I have no any data on my sdc(2) partition. I'm going to delete it or I can make a PV from it also. But, proceeding with deletion using parted.

```
[root@sysadmin ~]# parted /dev/sdc
GNU Parted 3.1
Using /dev/sdc
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) print
Model: VMware, VMware Virtual S (scsi)
Disk /dev/sdc: 42.9GB
Sector size (logical/physical): 512B/512B
Partition Table: msdos
Disk Flags:

Number Start End Size Type File system Flags
1 1049kB 10.7GB 10.7GB primary
2 10.7GB 32.2GB 21.5GB primary
(parted) rm 2
(parted) print
Model: VMware, VMware Virtual S (scsi)
Disk /dev/sdc: 42.9GB
Sector size (logical/physical): 512B/512B
Partition Table: msdos
Disk Flags:

Number Start End Size Type File system Flags
1 1049kB 10.7GB 10.7GB primary
```

9. Verify using "Isblk" command

10. Now extend "sdc1" using growpart utility.

```
[root@sysadmin ~]# growpart /dev/sdc 1
CHANGED: partition=1 start=2048 old: size=20971520 end=20973568 new: size=83883999 end=83886047
```

11. List all the disks and partitions again.

12. Now, we have to resize our PV (sdc1) to make the free space available.

pvresize /dev/sdc1

```
[root@sysadmin ~]# pvresize /dev/sdc1
Physical volume "/dev/sdc1" changed
1 physical volume(s) resized or updated / 0 physical volume(s) not resized
```

13. Confirm the new free space using "pvs" command.

```
[root@sysadmin ~]# pvs
PV VG Fmt Attr PSize PFree
/dev/sda2 centos_vm lvm2 a-- <59.00g 4.00m
/dev/sdb sysadmin_VG_1 lvm2 a-- <15.00g 0
/dev/sdc1 sysadmin_VG_1 lvm2 a-- <40.00g 30.00g
```

- 14. Here, it is confirmed that free space has been available.
- 15. Let's confirm the same available to VG.

16. Proceed for extending the size of LV of "sysadmin_VG_1" lvresize -L <+|-><size> <vg-name>/<lv-name>

17. Let's first confirm our current LV size.

NAME	MAJ:MIN	RM	SIZE	RO	TYPE	MOUNTPOINT
sda	8:0	0	60G	0	disk	
—sda1	8:1	0	1G	0	part	/boot
∟sda2	8:2	0	59G	0	part	
-centos_vm-root	253:0	0	38.3G	0	lvm	/
—centos_vm-swap	253:1	0	2G	0	lvm	[SWAP]
└─centos_vm-home	253:3	0	18.7G	0	lvm	/home
sdb	8:16	0	15G	0	disk	
└─sysadmin_VG_1-sysadmin_LV_1	253:2	0	25G	0	lvm	
sdc	8:32	0	40G	0	disk	
└─sdc1	8:33	0	40G	0	part	
Lsysadmin_VG_1-sysadmin_LV_1	253:2	0	25G	0	lvm	
sr0	11:0	1	1024M	0	rom	

18. Current LV size is 25 GB. Let's extend it to 55 GB.

```
[root@sysadmin ~]# lvresize -L +30GB sysadmin_VG_1/sysadmin_LV_1
Size of logical volume sysadmin_VG_1/sysadmin_LV_1 changed from 24.99 GiB (6398 extents) to 54.99 GiB (1407
8 extents).
Logical volume sysadmin_VG_1/sysadmin_LV_1 successfully resized.
```

19. You need to use the resize the filesystem after extending a LVM to ensure that the filesystem recognizes and utilizes the additional space. For LVM, "resize2fs" will be used.

resize2fs /dev/<vg-name>/<lv-name>

```
[root@sysadmin ~]# resize2fs /dev/sysadmin_VG_1/sysadmin_LV_1 resize2fs 1.42.9 (28-Dec-2013) Filesystem at /dev/sysadmin_VG_1/sysadmin_LV_1 is mounted on /sysadmin_mountpoint; on-line resizing required old_desc_blocks = 4, new_desc_blocks = 7 The filesystem on /dev/sysadmin_VG_1/sysadmin_LV_1 is now 14415872 blocks long.
```

20. Verify using "df -h"

```
root@svsadmin ~]# df -h
ilesystem
                                         Size Used Avail Use% Mounted on
                                                  0 475M
devtmpfs
                                                             0% /dev
tmpfs
                                                             0% /dev/shm
                                         487M
                                                     487M
tmpfs
tmpfs
                                         487M
                                                             0% /sys/fs/cgroup
dev/mapper/centos_vm-root
                                                             5% /
                                               1.6G
                                                       37G
/dev/mapper/centos_vm-home
dev/sda1
                                        1014M
                                                169M
                                                      846M
                                                            17% /boot
mpfs
                                          98M
                                                             0% /run/user/0
dev/mapper/sysadmin_VG_1-sysadmin_LV_1
                                                             1% /sysadmin_mountpoint
```

Case III: Extend an existing LV by adding another drive to a machine:

1. First verify the LV that needs to be extended is part of which volume group using "lvs".

```
[root@sysadmin ~]# lvs
LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
home centos_vm -wi-ao---- <18.70g
root centos_vm -wi-ao---- <38.30g
swap centos_vm -wi-ao---- 2.00g
sysadmin_LV_1 sysadmin_VG_1 -wi-ao---- 54.99g
```

- 2. I want to increase the space of "sysadmin_LV_1" which is a part of volume group "sysadmin_VG_1".
- Let's check, if "sysadmin_VG_1" volume group has free space available using "vgs" & "pvs" command.

- 4. Here above you can see that our VG has no space left. We have to attached another hard drive to our machine.
- 5. Below you can see that I have attached disk "sdd" of space (5 GB).

```
[root@sysadmin ~] # lsblk

NAME

MAJ:MIN RM SIZE RO TYPE MOUNTPOINT

sda 8:0 0 60G 0 disk

-sda1 8:1 0 1G 0 part /boot

-sda2 8:2 0 59G 0 part

-centos_vm-root 253:0 0 38.3G 0 lvm /

-centos_vm-swap 253:1 0 2G 0 lvm [SWAP]

-centos_vm-home 253:3 0 18.7G 0 lvm /home

sdb 8:16 0 15G 0 disk

-sysadmin_VG_1-sysadmin_LV_1 253:2 0 55G 0 lvm /sysadmin_mountpoint

sdc 8:32 0 40G 0 disk

-sdc1 8:33 0 40G 0 part

-sysadmin_VG_1-sysadmin_LV_1 253:2 0 55G 0 lvm /sysadmin_mountpoint

sdc 8:38 0 5G 0 disk

-sysadmin_VG_1-sysadmin_LV_1 253:2 0 55G 0 lvm /sysadmin_mountpoint

sdc 8:38 0 5G 0 disk

-sysadmin_VG_1-sysadmin_LV_1 1253:2 0 55G 0 lvm /sysadmin_mountpoint

sdc 1:0 1 1024M 0 rom
```

If the changes is not reflect, follow the step 5 of SECTION 1.1, to rescan all the SCSI hosts.

6. Let's create a PV from this newly attached drive.

pvcreate /dev/sdd

```
[root@sysadmin ~]# pvcreate /dev/sdd
  Physical volume "/dev/sdd" successfully created.
[root@sysadmin ~]# |
```

7. List all the PV(s) to confirm.

8. Now extend the VG "sysadmin VG 1" using the newly created PV (sdd)

vgextend sysadmin_VG_1 /dev/sdd

9. Confirm by listing the available VG(s) and check the free space.

21. Proceed for extending the size of LV of "sysadmin_VG_1"

lvresize -L <+ | -><size> <vg-name>/<lv-name>

22. Let's first confirm our current LV size.

```
[root@sysadmin ~]# lsblk
                                 MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
                                             60G 0 disk
                                          0 59G 0 part
0 38.3G 0 lvm
 sda2
                                 253:0
                                                           [SWAP]
  -centos_vm-swap
                                 253:1
                                                   0 lvm
  -centos vm-home
                                          0 18.7G
                                                           /home
                                 253:3
-sysadmin_VG_1-sysadmin_LV_1
                                             55G 0 lvm /sysadmin_mountpoint
                                              40G
55G
5G
 Lsysadmin_VG_1-sysadmin_LV_1 253:2
                                                   0 lvm /sysadmin_mountpoint
                                                   0 disk
                                  8:48
```

Current LV size is 55 GB. Let's extend it to 60 GB.

```
[root@sysadmin ~]# lvresize -L +4.9GB sysadmin_VG_1/sysadmin_LV_1
Rounding size to boundary between physical extents: 4.90 GiB.
Size of logical volume sysadmin_VG_1/sysadmin_LV_1 changed from 54.99 GiB (14078 extents) to 59.89 GiB (153
33 extents).
Logical volume sysadmin_VG_1/sysadmin_LV_1 successfully resized.
```

24. You need to use the resize the filesystem after extending a LVM to ensure that the filesystem recognizes and utilizes the additional space. For xfs LVM, "xfs_growfs" will be used. For ext4 LVM, "resize2fs" will be used.

resize2fs /dev/<vg-name>/<lv-name>

```
[root@sysadmin ~]# resize2fs /dev/sysadmin_VG_1/sysadmin_LV_1
resize2fs 1.42.9 (28-Dec-2013)
Filesystem at /dev/sysadmin_VG_1/sysadmin_LV_1 is mounted on /sysadmin_mountpoint; on-line resizing required
old_desc_blocks = 7, new_desc_blocks = 8
The filesystem on /dev/sysadmin_VG_1/sysadmin_LV_1 is now 15700992 blocks long.
```

25. Verify using "df -h"

```
[root@sysadmin ~]# df -h
                                         Size Used Avail Use% Mounted on
devtmpfs
                                                 0 475M
                                                           0% /dev
tmpfs
                                                            0% /dev/shm
                                                            2% /run
tmpfs
                                                            0% /sys/fs/cgroup
                                               1.6G
/dev/mapper/centos_vm-root
                                                            5% /
dev/mapper/centos_vm-home
                                                     846M
                                        1014M
```

Case IV: Extend an existing LV by reducing another LV of the same VG:

Reduction:

1. First verify the LV that needs to be reduced is part of which volume group using "lvs".

```
[root@sysadmin ~]# lvs
LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
home centos_vm -wi-ao---- <18.70g
root centos_vm -wi-ao---- <38.30g
swap centos_vm -wi-ao---- 2.00g
sysadmin_LV_1 sysadmin_VG_1 -wi-a---- 49.89g
sysadmin_LV_2 sysadmin_VG_1 -wi-a---- 10.00g
```

- 2. I want to decrease the space of "sysadmin_LV_2" which is a part of volume group "sysadmin_VG_1".
- 3. Let's check, if "sysadmin_VG_1" volume group has free space available using "vgs" command.

- 4. Here above you can see that our VG has almost no space left. What we are going to do is to decrease the space the "sysadmin_LV_2" and increase space of "sysadmin_LV_1" of the same VG.
- 5. First verify the all the drives and partitions.

```
MAJ:MIN RM
                                                SIZE RO TYPE MOUNTPOINT
                                                60G 0 disk
                                                1G 0 part /boot
59G 0 part
8.3G 0 lvm /
sda2
  -centos_vm-root
                                            0 38.3G
                                            0 2G
0 18.7G
                                                               [SWAP]
  -centos_vm-home
                                  253:4
                                                      0 disk
                                    8:16
                                             0 49.9G
                                                       0 disk
                                     8:33
                                                       0 part
 -sysadmin_VG_1-sysadmin_LV_1
                                                       0 disk
-sysadmin_VG_1-sysadmin_LV_2
                                                       0 lvm
```

6. Here current size of "sysadmin_LV_2" is (10 GB). I'm reducing it to (5 GB). If the LVM is mounted make sure to unmount it first before actual reduction. In my case it is already unmounted.

```
[root@sysadmin ~]# lvs
LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
home centos_vm -wi-ao---- <18.70g
root centos_vm -wi-ao---- <28.30g
swap centos_vm -wi-ao---- 2.00g
sysadmin_LV_1 sysadmin_VG_1 -wi-a---- 49.89g
sysadmin_LV_2 sysadmin_VG_1 -wi-a---- 10.00g
```

7. Let's check the FS for any errors. Depending on the filesystem type, you can use commands like "fsck.ext4" or "xfs repair"

fsck.ext4 /dev/<vg-name>/<lv-name>

```
[root@sysadmin ~]# fsck.ext4 /dev/sysadmin_VG_1/sysadmin_LV_2
e2fsck 1.42.9 (28-Dec-2013)
/dev/sysadmin_VG_1/sysadmin_LV_2: clean, 11/655360 files, 83137/2621440 blocks
```

8. You need to use the resize the filesystem after extending a LVM to ensure that the filesystem recognizes and utilizes the additional space. For xfs LVM, "xfs_growfs" will be used. For ext4 LVM, "resize2fs" will be used.

resize2fs /dev/<vg-name>/<lv-name> <size in MB(s)>

```
[root@sysadmin ~]# resize2fs /dev/sysadmin_VG_1/sysadmin_LV_2 5012M
resize2fs 1.42.9 (28-Dec-2013)
Resizing the filesystem on /dev/sysadmin_VG_1/sysadmin_LV_2 to 1283072 (4k) blocks.
The filesystem on /dev/sysadmin_VG_1/sysadmin_LV_2 is now 1283072 blocks long.
```

9. Let's decrease the size of LV.

lvresize -L <-><size> <vg-name>/<lv-name>

```
[root@sysadmin ~]# lvresize -L -5GB sysadmin_VG_1/sysadmin_LV_2
WARNING: Reducing active logical volume to 5.00 GiB.
THIS MAY DESTROY YOUR DATA (filesystem etc.)
Do you really want to reduce sysadmin_VG_1/sysadmin_LV_2? [y/n]: y
Size of logical volume sysadmin_VG_1/sysadmin_LV_2 changed from 10.00 GiB (2560 extents) to 5.00 GiB (1280 extents).
Logical volume sysadmin_VG_1/sysadmin_LV_2 successfully resized.
```

10. Let's check, if "sysadmin_VG_1" volume group has free space available using "vgs" command.

11. Here above you can see that our VG has now 5 GB free space available. Let's allocate it to the "sysadmin_LV_1" of the same VG.

lvresize -L <+><size> <vg-name>/<lv-name>

```
[root@sysadmin ~]# lvresize -L +5.09GB sysadmin_VG_1/sysadmin_LV_1
Rounding size to boundary between physical extents: 5.09 GiB.
Size of logical volume sysadmin_VG_1/sysadmin_LV_1 changed from 49.89 GiB (12773 extents) to <54.99 GiB (14
077 extents).
Logical volume sysadmin_VG_1/sysadmin_LV_1 successfully resized.
```

12. You need to use the resize the filesystem after extending a LVM to ensure that the filesystem recognizes and utilizes the additional space. For xfs LVM, "xfs_growfs" will be used. For ext4 LVM, "resize2fs" will be used. Perform diskcheck if needed.

resize2fs /dev/<vg-name>/<lv-name>

```
[root@sysadmin ~]# e2fsck -f /dev/sysadmin_VG_1/sysadmin_LV_1
e2fsck 1.42.9 (28-Dec-2013)
Pass 1: Checking inodes, blocks, and sizes
Pass 2: Checking directory structure
Pass 3: Checking directory connectivity
Pass 4: Checking reference counts
Pass 5: Checking group summary information
/dev/sysadmin_VG_1/sysadmin_LV_1: 11/3270400 files (0.0% non-contiguous), 251390/13079552 blocks
[root@sysadmin ~]#
[root@sysadmin ~]#
[root@sysadmin ~]# resize2fs /dev/sysadmin_VG_1/sysadmin_LV_1
resize2fs 1.42.9 (28-Dec-2013)
Resizing the filesystem on /dev/sysadmin_VG_1/sysadmin_LV_1 to 14414848 (4k) blocks.
The filesystem on /dev/sysadmin_VG_1/sysadmin_LV_1 is now 14414848 blocks long.
```

- 13. Remount all the LVM(s)
- 14. Verify using "df -h"

```
root@sysadmin ~]# df -h
Filesystem
                                         Size Used Avail Use% Mounted on
devtmpfs
                                         475M
                                                0 475M 0% /dev
tmpfs
                                         487M
                                                     487M
tmpfs
                                                            0% /sys/fs/cgroup
                                         487M
                                                     487M
tmpfs
/dev/mapper/centos_vm-root
                                               1.6G
                                                            5% /
                                          39G
                                                      37G
/dev/sda1
                                        1014M
                                                     846M
                                                           17% /boot
/dev/mapper/centos_vm-home
                                          19G
                                                            1% /home
tmpfs
                                          98M
                                                      98M
                                                            0% /run/user/0
                                                 0
                                                            1% /sysadmin_mountpoint
/dev/mapper/sysadmin_VG_1-sysadmin_LV_1
                                         55G
/dev/mapper/sysadmin_VG_1-sysadmin_LV_2 4.8G
                                                     4.5G
                                                            1% /sysadmin_mountpoint1
```


15. Above you can see that LVM_1 space has been increased from 50GB to 55GB and LVM_2 space has been decreased from 10GB to 5 GB

Note: Working with LVM reductions can result in data-loss or LVM corruption. It is always recommended to backups all the important data when reducing the LVM(s).

3. Stripped LVM Partitioning

A linear logical volume consists of a single physical volume or a concatenation of multiple physical volumes. It's the simplest form of logical volume in LVM, where the data is stored sequentially across the underlying physical volumes.

A striped logical volume, also known as a RAID-0 logical volume, distributes data across multiple physical volumes in a striped manner. The data is divided into chunks or stripes, which are then distributed evenly across the physical volumes. This provides improved performance by allowing simultaneous read and write operations across multiple disks.



The stripe size refers to the amount of data that is written to a single physical volume (PV) before moving on to the next one. It determines the size of each individual stripe within the striped LV.

3.1 Steps to create stripped LV from VG:

1. First, check the available disks on your machine using "lsblk" command.

```
[root@sysadmin ~]# lsblk
                  MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
NAME
sda
                   8:0 0
                              60G 0 disk
                    8:1
                               1G 0 part /boot
 -sda1
                            59G
                    8:2
                                   0 part
                         0 38.3G
  -centos_vm-root 253:0
                                   0 lvm
   -centos_vm-swap 253:1
                                          [SWAP]
                                   0 lvm
                          0
  _centos_vm-home 253:2
                          0 18.7G
                                  0 lvm
                                          /home
sdb
                    8:16
                              10G 0 disk
sdc
                    8:32
                          0
                              10G 0 disk
sdd
                   8:48
                          Θ
                              20G 0 disk
                   11:0
                          1 1024M 0 rom
```

- 2. Here above, we have three disks "sdb,sdc,sdd" are available for use.
- 3. Let create physical volume from these drives and verify using "pvs" command.

pvcreate /dev/sd[b-d]

```
[root@sysadmin ~]# pvcreate /dev/sd[b-d]
 Physical volume "/dev/sdb" successfully created.
 Physical volume "/dev/sdc" successfully created.
 Physical volume "/dev/sdd" successfully created
[root@sysadmin ~]# pvs
                     Fmt Attr PSize
                                       PFree
 /dev/sda2 centos_vm lvm2 a-- <59.00g 4.00m
                     lvm2 ---
                              10.00g 10.00g
 /dev/sdb
                     lvm2 ---
 /dev/sdc
                                10.00g 10.00g
                     lvm2 ---
                                20.00g 20.00g
```

4. Create volume group from these PV(s) and verify newly created VG using "vgs" command.

vgcreate sysadmin_VG_1 /dev/sd[b-d]

Let's create stripped LV from newly created VG "sysadmin_VG_1". The below command creates a LV of 27G from VG total space of 40 GB, with used stripes(drives) = 3, stipe-size = 1MB each.

lvcreate --stripes 3 --stripesize 1M -L 27G -n sysadmin_SLV_1 sysadmin_VG_1

```
LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
              -wi-ao---- <38.30g
root
       centos_vm
```

You can check the devices and extents used by stripped LV using "Ivdisplay -v <Iv-name>".

```
[root@sysadmin ~]# lvdisplay -m /dev/sysadmin_VG_1/sysadmin_SLV_1
 LV Path
LV Name
                                sysadmin_SLV_1
sysadmin_VG_1
N1Li08-7Haf-29Ue-lzw6-fmGE-Yns7-vZ4w1n
 VG Name
 LV Creation host, time sysadmin, 2023-06-03 04:40:35 +0500 LV Status available
 # open
LV Size
  Segments
 Read ahead sectors
- currently set to
 Block device
 --- Segments ---
Logical extents 0 to 6911:
    Stripes
    Stripe 0:
Physical volume
      Physical extents 0 to 2303
    Stripe 1:
      Physical volume /dev/sdc
Physical extents 0 to 2303
      Physical volume /dev/sdd
Physical extents 0 to 2303
```

7. Let's format the stripped LV with ext4 FS.

mkfs.ext4 /dev/<vg-name>/<lv-name>

```
root@sysadmin ~]# mkfs.ext4 /dev/sysadmin_VG_1/sysadmin_SLV_1
 nke2fs 1.42.9 (28-Dec-2013)
Filesystem label=
OS type: Linux
 US type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=256 blocks, Stripe width=768 blocks
1769472 inodes, 7077888 blocks
353894 blocks (5.00%) reserved for the super user
 First data block=0
Maximum filesystem blocks=2155872256
216 block groups
32768 blocks per group, 32768 fragments per group
20192 inodes per group
Superblock backups stored on blocks:
32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632, 2654208,
4096000
Allocating group tables: done
Writing inode tables: done
Creating journal (32768 blocks): done
Writing superblocks and filesystem accounting information: done
```

You can verify using blkid command.

```
[root@sysadmin ~]# blkid /dev/sysadmin_VG_1/sysadmin_SLV_1
dev/sysadmin_VG_1/sysadmin_SLV_1: UUID="4531ae5e-d3cb-49b6-8a8a-b1345f6003c4" TYPE="ext4"/
[root@sysadmin ~]#
```

9. We can also create linear LV along with stripped LV on same VG.

lvcreate -L 12.988GB -n sysadmin_LLV_1 sysadmin_VG_1

```
[root@sysadmin ~]# lvcreate -L 12.988GB -n sysadmin_LLV_1 sysadmin_VG_1
 Rounding up size to full physical extent <12.99 GiB
 Logical volume "sysadmin_LLV_1" created.
```

10. Let's mount the stripped LV created above to a mount location.

mount -t ext4 /dev/<vg-name>/<lv-name>

```
devtmpfs
                                            475M
                                                        475M
                                                                0% /dev
tmpfs
                                            487M
                                                                0% /dev/shm
                                                        487M
tmpfs
                                            487M
                                                  7.7M
                                                        479M
                                                                2% /run
                                            487M
                                                                0% /sys/fs/cgroup
tmpfs
                                                     0
                                                        487M
/dev/mapper/centos_vm-root
                                             39G
                                                  1.6G
/dev/sda1
                                           1014M
                                                  169M
                                                         846M
                                                               17% /boot
/dev/mapper/centos_vm-home
                                             19G
                                                   33M
                                                         19G
                                                                1% /home
                                                          98M
                                                                0% /run/user/0
/dev/mapper/sysadmin_VG_1-sysadmin_SLV_1
                                                   45M
                                             27G
                                                          26G
                                                                   /stripped_mount
```

3.2 Steps to extend a stripped LV.

To increase the size of striped logical volume, there must be enough free space on the underlying physical volumes that make up the volume group to support the stripe. For example, if you have a two-way stripe that that uses up an entire volume group, adding a single physical volume to the volume group will not enable you to extend the stripe. Instead, you must add at least two physical volumes to the volume group.

1. First, verify VG free space and list all the LVM using "lvs" command.

Let's try extending the stripped LV.

lvextend /dev/<vg-name>/<lv-name> -L <size>

```
[root@sysadmin ~]# lvextend /dev/sysadmin_VG_1/sysadmin_SLV_1 -L +3GB
Using stripesize of last segment 1.00 MiB
Insufficient suitable allocatable extents for logical volume sysadmin_SLV_1: 3 more required
```

- 3. You can see above that, we can't able to extend. Based on required extents we need at-least two new physical disks.
- 4. Let's extend our VG by attaching another 2 PV(s) to our volume group. I have already attached a new physical disk (sde,sdf) of 30GB,5GB respectively to our machine.

pvcreate /dev/sd[e-g] vgextend <vg-name> /dev/sd[e-g]

```
[root@sysadmin ~]# pvcreate /dev/sd[e-f]
  Physical volume "/dev/sde" successfully created.
  Physical volume "/dev/sdf" successfully created.
[root@sysadmin ~]# vgextend sysadmin_VG_1 /dev/sd[e-f]
  Volume group "sysadmin_VG_1" successfully extended
```

5. Let' check the LV segments first.

lvdisplay -m /dev/sysadmin_VG_1/sysadmin_SLV_1 | tail -17

6. Now, try extending the stripped LV again.

lvextend /dev/<vg-name>/<lv-name> -L +<size>

```
[root@sysadmin ~]# lvextend /dev/sysadmin_VG_1/sysadmin_SLV_1 -L +10G
Using stripesize of last segment 1.00 MiB
Rounding size (9472 extents) up to stripe boundary size for segment (9474 extents).
Size of logical volume sysadmin_VG_1/sysadmin_SLV_1 changed from 27.00 GiB (6912 extents) to <37.01 GiB (9474 extents)

Logical volume sysadmin_VG_1/sysadmin_SLV_1 successfully resized.
```

7. Now LV has been successfully extended.

Note: You can also reduce stripped LV size, but since data resides on different PV(s), so it's not wise to reduce this LVM.