x86 Assembly Programming

Azlan Mukhtar

- x86 Basic Architecture
- Introduction
- Endianness
- Registers and Flags
- Memory Addressing
- Stacks
- Signed number representations

- Assembly Programming
 - Data movement
 - Arithmetic operation
 - Control structure
 - Bitwise operation
 - Data/Array manipulations
 - Assembler

Introduction to x86

- Started with 8086 in 1978
- Continued with 8088, 80186, 80286, 386, 486, Pentium, 686... Intel Core
- CISC architecture
- 32-bit is called x86-32 or IA-32
- 64-bit is called x86-64, AMD64, Intel 64

Intel 80386

- Introduced in 1986
- Has a 32-bit word length
- Has eight general-purpose registers
- Supports paging and virtual memory
- Addresses up to 4GiB of memory
- Base for current x86 32 bit architecture

Byte Order/Endianness

- Little Endian
 - On memory: 78 56 34 12
 - Actual value: 0x12345678
- Big Endian
 - On Memory: 12 34 56 78
 - Actual value: 0x12345678

String Styles

• ASCIIZ - C-style

```
H e l l o
48 65 6C 6C 6F 00
```

Null-terminated Unicode

```
H e l l o 48 00 65 00 6C 00 6C 00 6F 00 00
```

Pascal

Delphi

05 00 00 00 48 65 6C 6C 6F

Data Register Layout

General-Purpose Registers

31	16	15	8	7	0	16-bit	32-bit
		AH		AL		AX	EAX
		BH		BL		BX	EBX
		CH		CL		CX	ECX
		DH		DL		DX	EDX
			BF				EBP
			SI				ESI
			DI				EDI
		SP				ESP	

Register Layout - Example

- EAX = 12345678h
- AX = 5678h
- AH = 56h
- AL = 78h

EAX							
1	2 3 4 5 6 7 8						
				A	Н	А	Ĺ
					A	X	

^{*} h is for hexadecimal notation

Data Registers

Register	Description	Usage
AL/AH/AX/EAX	Accumulator Register	Arithmetic operations
BL/BH/BX/EBX	Base register	General data storage, index
CL/CH/CX/ECX	Counter register	Loop constructs
DL/DH/DX/EDX	Data register	Arithmetic

Data Register - Example

- Accumulator
- ADD EAX, EBX; add the value in EBX and EAX, and store the result into EAX
 SUB EAX, EBX; substitute the value in EBX from EAX, and store the result into EAX
 IMUL EAX, EBX; multiply EAX and EBX, and store the result into EAX; into EAX
- More about this later

Address Registers

Register	Description	Usage
IP / EIP	Instruction Pointer	Program execution counter
SP / ESP	Stack Pointer	ESP will hold an offset to top of stacks memory location
BP / EBP	Base Pointer	Stack frame
SI / ESI	Source Index	String operation
DI / EDI	Destination Index	String operation


Segment Registers

Register	Description	Usage
CS	Code Segment	Program code
DS	Data Segment	Program data
SS	Stack Segment	Stack
ES/FS/GS	Other Segments	Other uses


Segment Registers

- Modern Operating System such as Windows, MacOSX, *nix are using protected mode flat model and segment registers are less relevant. CS, DS, SS, and ES are pointing to the same location, which is 0 offset.
- Windows NT is utilizing FS register to store Process Environment Block and Thread Information Block (TIB)
 - https://en.wikipedia.org/wiki/Process_Environment_Block
 - http://en.wikipedia.org/wiki/Win32_Thread_Information_Block

EFLAGS Register (bit 0 – 15)



EFLAGS Register (bit 16 – 31)



EFLAGS Register – Status Flags

- ZF Zero flag Set if the result is zero; cleared otherwise.
- SF Sign flag Set equal to the most-significant bit of the result, which is the sign bit of a signed integer. (0 indicates a positive value and 1 indicates a negative value.)
- CF Carry flag Set if an arithmetic operation generates a carry or a borrow out of the most significant bit of the result; cleared otherwise. This flag indicates an overflow condition for unsigned-integer arithmetic. It is also used in multiple-precision arithmetic.
- OF Overflow flag Set if the integer result is too large a positive number or too small a negative number (excluding the sign-bit) to fit in the destination operand; cleared otherwise. This flag indicates an overflow condition for signed-integer (two's complement) arithmetic.
- AF Adjust flag Set if an arithmetic operation generates a carry or a borrow out of bit 3 of the result; cleared otherwise. This flag is used in binary-coded decimal (BCD) arithmetic. (Rarely Used)
- PF Parity flag Set if the least-significant byte of the result contains an even number of 1 bits; cleared otherwise. (Rarely Used)

EFLAGS Registers – **DF FLAG**

- The direction flag (DF, located in bit 10 of the EFLAGS register) controls string instructions (MOVS, CMPS, SCAS, LODS, and STOS). Setting the DF flag causes the string instructions to auto-decrement (to process strings from high addresses to low addresses). Clearing the DF flag causes the string instructions to auto-increment (process strings from low addresses to high addresses).
- The STD and CLD instructions set and clear the DF flag, respectively.

EFLAGS Register – Flags Changing Instructions

- Instruction that affecting flags
 - ADD/SUB Modifies Flags: AF CF OF PF SF ZF
 - CMP- Modifies Flags: AF CF OF PF SF ZF
 - TEST Modifies Flags: CF OF PF SF ZF (AF undefined)
 - CLD/STD Modifies Flags: DF

Signed number representations – Two's Complement

• 8 bit two's complement

Binary Value	Hex Value	Two's Complement	Unsigned
00000000	0x00	0	0
00000001	0x01	1	1
01111110	0x7E	126	126
01111111	0x7F	127	127
10000000	0x80	-128	128
10000001	0x81	-127	129
10000010	0x82	-126	130
11111110	0xFE	-2	254
11111111	0xFF	-1	255

Two's Complement – How to convert

Method one

Steps	Example 1	Example 2
1. Starting from the right, find the first '1'	0101001	0101 1 00
2. Invert all of the bits to the left of that one	11010111	1010 100

Method two

Steps	00000001
1. Invert all the bits through the number	11111110
2. Add one	11111111

- Method three
 - Use x86 instruction for Two's Complement Negation, NEG
 - Example NEG EAX

Two's Complement - examples

Example 1:

```
mov al, 0x05
add al, 0xFE; 0xFE = -2 or 0xFE = 254
\Rightarrow al = 3
```

Example 2:

```
mov al, 0x02
add al, 0xFA; 0xFA = -6 or 0xFA = 250
\Rightarrow al = 0xFC; 0xFC = -4 or 0xFC = 252
```

Basic x86 Assembly instructions

- Data Transfers
- Arithmetic
- Logic
- Jumps
- Misc

Reading the x86 Manual (RTxM)

MOVZX - Move with Zero-Extend

0F B6 / r	MOVZX r16,r/m8	Move byte to word with zero-extension
0F B6 / r	MOVZX r32,r/m8	Move byte to doubleword, zero-extension
0F B7 / r	MOVZX r32,r/m16	Move word to doubleword, zero-extension

Description

Copies the contents of the source operand (register or memory location) to the destination operand (register) and zero extends the value to 16 or 32 bits. The size of the converted value depends on the operand-size attribute.

Operands Bytes Clocks reg, reg 3 NP

reg, mem 3+d(0,1,2,4) 3 NP

(Note: destination reg is 16 or 32-bits; source is 8 or 16 bits)

Flags

None.

Reading the x86 Manual – cont.

r	Any general register		
r8	One of the byte general-purpose registers AL, CL, DL, BL, AH, CH, DH, or BH.		
r16	One of the word general-purpose registers AX, CX, DX, BX, SP, BP, SI, or DI.		
r32	One of the doubleword general-purpose registers EAX, ECX, EDX, EBX, ESP, EBP, ESI, or EDI.		
m	A 16- or 32-bit operand in memory.		
m8	A byte operand in memory, usually expressed as a variable or array name, but pointed to by the DS:(E)SI or ES:(E)DI registers. This nomenclature is used only with the string instructions and the XLAT instruction.		
m16	A word operand in memory, usually expressed as a variable or array name, but pointed to by the DS:(E)SI or ES:(E)DI registers. This nomenclature is used only with the string instructions.		
And so on, please refer the docs.			

Data Transfer Instructions

- MOV Move data between general-purpose registers; move data between memory and general purpose or segment registers; move immediates to general-purpose registers
- MOVSX Move and sign extend
- MOVZX Move and zero extend
- PUSH Push onto stack
- POP Pop off of stack
- XCHG Exchange
- BSWAP Byte swap converts between 32 bit little endian and big endian values
- PUSHA/PUSHAD Push general-purpose registers onto stack
- POPA/POPAD Pop general-purpose registers from stack
- CWD/CDQ Convert word to doubleword/Convert doubleword to quadword
- CBW/CWDE Convert byte to word/Convert word to doubleword in EAX register

Binary Arithmetic Instructions

ADD - Integer add

NEG - Negate

- ADC Add with carry
- SUB Subtract
- SBB Subtract with borrow
- IMUL Signed multiply
- MUL Unsigned multiply
- IDIV Signed divide
- DIV Unsigned divide
- INC Increment
- DEC Decrement
- CMP Compare (Similar to SUB but the result is not stored (discarded) and the flags are changed)

Logical Instructions

- AND Perform bitwise logical AND
- OR Perform bitwise logical OR
- XOR Perform bitwise logical exclusive OR
- NOT Perform bitwise logical NOT

Shift and Rotate Instructions

- SAR Shift arithmetic right
- SHR Shift logical right
- SAL/SHL Shift arithmetic left/Shift logical left
- SHRD Shift right double
- SHLD Shift left double
- ROR Rotate right
- ROL Rotate left
- RCR Rotate through carry right
- RCL Rotate through carry left

Control Transfer Instructions

- JMP Jump
- JE/JZ Jump if equal/Jump if zero
- JNE/JNZ Jump if not equal/Jump if not zero
- JA/JNBE Jump if above/Jump if not below or equal
- JAE/JNB Jump if above or equal/Jump if not below
- JB/JNAE Jump if below/Jump if not above or equal
- JBE/JNA Jump if below or equal/Jump if not above
- JG/JNLE Jump if greater/Jump if not less or equal
- JGE/JNL Jump if greater or equal/Jump if not less
- JL/JNGE Jump if less/Jump if not greater or equal
- JLE/JNG Jump if less or equal/Jump if not greater
- JC Jump if carry

Control Transfer Instructions - continue

- JNC Jump if not carry
- JO Jump if overflow
- JNO Jump if not overflow
- JS Jump if sign (negative)
- JNS Jump if not sign (non-negative)
- JPO/JNP Jump if parity odd/Jump if not parity
- JPE/JP Jump if parity even/Jump if parity
- JCXZ/JECXZ Jump register CX zero/Jump register ECX zero
- LOOP Loop with ECX counter
- LOOPZ/LOOPE Loop with ECX and zero/Loop with ECX and equal
- LOOPNZ/LOOPNE Loop with ECX and not zero/Loop with ECX and not equal

Control Transfer Instructions - continue

- CALL Call procedure
- RET Return
- IRET Return from interrupt
- INT Software interrupt
- ENTER High-level procedure entry
- LEAVE High-level procedure exit

String Instructions

- MOVS/MOVSB Move string/Move byte string
- MOVS/MOVSW Move string/Move word string
- MOVS/MOVSD Move string/Move doubleword string
- CMPS/CMPSB Compare string/Compare byte string
- CMPS/CMPSW Compare string/Compare word string
- CMPS/CMPSD Compare string/Compare doubleword string
- SCAS/SCASB Scan string/Scan byte string
- SCAS/SCASW Scan string/Scan word string
- SCAS/SCASD Scan string/Scan doubleword string

String Instructions - Continue

- LODS/LODSB Load string/Load byte string
- LODS/LODSW Load string/Load word string
- LODS/LODSD Load string/Load doubleword string
- STOS/STOSB Store string/Store byte string
- STOS/STOSW Store string/Store word string
- STOS/STOSD Store string/Store doubleword string
- REP Repeat while ECX not zero
- REPE/REPZ Repeat while equal/Repeat while zero
- REPNE/REPNZ Repeat while not equal/Repeat while not zero

Miscellaneous Instructions

- LEA Load effective address
- NOP No operation

Examples of Mnemonics

mnemonic argument1, argument2, argument3			
MOV EAX, 1	Move 1 to EAX		
ADD EDX, 5	Add 5 to EDX		
SUB EBX, 2	Subtract 2 from EBX		
AND ECX, 0	Bit-wise AND 0 to ECX		
XOR EDX, 4	Bit-wise eXclusive OR 4 to EDX		
SHL ECX, 6	Shift ECX left by six		
ROR EBX, 3	Bit-wise rotate EBX right by 3		
INC ECX	Increment ECX		

Addressing Memory

mov eax, [ebx]
; Move the 4 bytes in memory at the address contained in EBX into EAX
mov [var], ebx
; Move the contents of EBX into the 4 bytes at memory address var.
(Note, var is a 32-bit constant).
mov eax, [esi-4]
; Move 4 bytes at memory address ESI + (-4) into EAX
mov [esi+eax], cl
; Move the contents of CL into the byte at address ESI+EAX
mov edx, [esi+4*ebx]
; Move the 4 bytes of data at address ESI+4*EBX into EDX

Addressing Memory – With Size Directive

- mov BYTE PTR [ebx], 2
 ; Move 2 into the single byte at the address stored in EBX.
- mov WORD PTR [ebx], 2
 ; Move the 16-bit integer representation of 2 into the 2 bytes starting at the address in EBX.
- mov DWORD PTR [ebx], 2
 ; Move the 32-bit integer representation of 2 into the 4 bytes starting at the address in EBX.

Microsoft Macro Assembler

- Why MASM
 - Free (comes with Visual C++ Express/Community)
 - Visual Studio IDE for Coding and Debugging

Microsoft Macro Assembler (MASM)

```
.386
.model flat, stdcall
option casemap : none ; case sensitive
include \masm32\include\windows.inc
include \masm32\include\user32.inc
include \masm32\include\kernel32.inc
includelib \masm32\lib\user32.lib
includelib \masm32\lib\kernel32.lib
.data
szTitle db 'Win32', 0
szMessage db 'Hello World', 0
.code
start:
push 0
                        ; uType = MB OK
push offset szTitle ; LPCSTR lpCaption
push offset szMessage ; LPCSTR lpText
push 0
                        ; hWnd = HWND DESKTOP
call MessageBoxA
push 0
call ExitProcess
end start
```

Netwide Assembler (NASM) - Alternative

```
; Assemble: nasm -f win32 hello nasm.asm
; Link: link hello_nasm.obj user32.lib /entry:main
; (using Visual C++'s linker)
extern MessageBoxA@16
segment .text
global main
main:
         push dword 0     ; uType = MB_OK
         push szTitle ; LPCSTR lpCaption
         push szMessage ; LPCSTR lpText
         push dword 0 ; hWnd = HWND DESKTOP
         call MessageBoxA@16
         ret
segment .data
szMessage: db 'Hello World',0
szTitle: db 'Program Title',0
```

FASM - Arithmetic - Alternative

```
format PE Console 4.0
entry start
include 'win32a.inc'
section '.text' code readable executable
 start:
 xor eax, eax
 add eax, 8
 mov ecx, 2
 sub eax, ecx
 mul ecx
 push eax
 push szResult
 call [printf]
 add esp, 8
 ret
section '.data' data readable writeable
 szResult db "The result is: %d",10,0
section '.idata' import data readable
library msvcrt,'msvcrt.dll'
import msvcrt,\
printf,'printf'
```

Procedure & Calling Conventions

- Procedure Call
- Global & Local Variables
- CDECL
- STDCALL
- FASTCALL

Procedure Call

- Procedural programming is derived from structured programming, based upon the concept of the procedure call
- Procedures, also known as routines, subroutines, methods, or functions
- x86 architecture supports procedure call
- The processor supports procedure calls in the following two different ways:
- CALL and RET instructions.
- ENTER and LEAVE instructions, in conjunction with the CALL and RET instructions
- The procedure stack, commonly referred to simply as "the stack", will save the state of the calling procedure, **pass parameters** to the called procedure, and **store local variables** for the currently executing procedure

Global And Local Variable

```
// global_var.c
                          Compilation cmd line:
                          cl global_var.c /Faglobal_var.asm
#include <stdio.h>
int global_var1 = 5;
int main ()
  int local_var1 = 1;
  int local_var2 = 2;
  int result = 0;
  result = global_var1 + local_var1 + local_var2;
  return 0;
```

CDECL

```
// C/C++ codes
_cdecl int MyFunction1(int a,
int b)
 return a + b;
 x = MyFunction1(2, 3);
```

```
; x86 asm codes
_MyFunction1:
push ebp
mov ebp, esp
mov eax, [ebp + 8]
mov edx, [ebp + 12]
add eax, edx
pop ebp
ret
Start:
push 3
push 2
call _MyFunction1
add esp, 8 ; clean up
```

STDCALL

```
// C/C++ codes
stdcall int
MyFunction2(int a, int b)
   return a + b;
 x = MyFunction2(2, 3);
```

```
: x86 asm codes
: MyFunction@8
push ebp
mov ebp, esp
mov eax, [ebp + 8]
mov edx, [ebp + 12]
add eax, edx
pop ebp
ret 8
               ; clean up
Start:
push 3
push 2
call MyFunction@8
```

FASTCALL

```
// C/C++ codes
_fastcall int
MyFunction3(int a, int b)
{
   return a + b;
}
x = MyFunction3(2, 3);
```

```
: x86 asm codes
:@MyFunction3@8
push ebp
add eax, edx
;a is in eax, b is in edx
pop ebp
ret
Start:
mov eax, 2
mov edx, 3
call @MyFunction3@8
```

References

Intel® 64 and IA-32 Architectures Software Developer Manuals

http://www.intel.com/content/www/us/en/processors/architecturessoftware-developer-manuals.html

80x86 Instruction Set (simplified)

http://www.penguin.cz/~literakl/intel/intel.html

80x86 Instruction Set cheatsheet

http://www.jegerlehner.ch/intel/

x86 Assembly

http://en.wikibooks.org/wiki/X86_Assembly

http://en.wikibooks.org/wiki/X86_Disassembly

http://www.cs.virginia.edu/~evans/cs216/guides/x86.html