Bijlage 16

Windvi User's Manual

Fabrice Popineau Fabrice.Popineau@supelec.fr

Editor's note

This article is an adaptation of the HTML file that comes with the current version (0.40) of windvi.

Why another Windows dvi viewer?

Note that throughout this document, when I say 'Win32', this means Windows 9x and Windows NT.

There are many previewers for dvi files under Win32. The most popular is probably Dviwin by H. Sendoukas. However it lacks some important features:

- □ the ability to recursively search directories for font files,
- □ the ability to use .vf files or display PostScript fonts.

Unfortunately, the Dviwin sources were never put into the public domain; on the other side of the fence, Xdvi under Unix has these features, is widely used and its sources are available. Xdvi(k) uses the kpathsea library to search directories, already used in the Web2c-win32 port of TeX, so there was some interest in porting Xdvi(k) to Win32. As it turned out, this turned into far more than just a port, as X Windows is far from Win32. All the user interface and the graphical part has been rewritten.

For the future, when the base functionality of Xdvi(k) is available and stable under Win32, we can expect to add the interesting features of Dviwin to Windvi.

Features

The most important features of Windvi are as follows:

- monochrome or grey scale bitmaps (antialiasing) for fonts.
- easy navigation through the dvi file
 - page by page,
 - with different increments (by 5 or 10 pages at a time)
 - goto home, end, or any page within the document,
- □ different shrink factors to zoom page in and out,
- □ magnifying glass to show the page at the pixel level,
- use of .vf fonts
- □ display .pk .gf font files

- automatic generation of missing PK files even for PostScript fonts,
- □ tracking dvi file changes, and automatic reopening
- understanding Omega extended dvi files,
- □ drag-and-drop file from the Windows shell explorer,
- □ some color support (foreground and background),

Installation

The home of Windvi

Windvi is part of the Web2c package for win32. You will find the whole Web2C package on any CTAN archive, for example:

ftp://ftp.tex.ac.uk/pub/tex/systems/win32/
web2c

Beta versions of Web2C for Win32 are available from: ftp://ftp.ese-metz.fr/pub/TeX/win32-beta

If you want to retrieve only the windvi distribution, you should get:

ftp://ftp.tex.ac.uk/pub/tex/systems/win32/
web2c/windvixx.zip for the standalone released version;

ftp://ftp.ese-metz.fr/pub/TeX/win32-beta/
windvixx.zip for beta versions, xx being always as high
as possible.

Announcements of beta version are made through the texk-win32 mailing-list. Subscriptions can be sent to texk-win32-request@ese-metz.fr. Send 'help' in the subject for more information.

Unpacking


Assuming you have retrieved one of the windvixx.zip files, you will have to unpack it at the ¡root; of some TDS conformant texmf tree like this one:

```
<root>/bin/win32
    /texmf/
    /dvips
    /tex
    /latex
/web2c
```

- □ owindvi.exe, windvi.exe, mktex*.exe and gsftopk.exe go to bin/win32
- □ render.ps (used by gsftopk) goes to texmf/dvips
- □ texmf.cnf and mktex.cnf go to texmf/web2c.

146 MAPS

Windvi User's Manual Bijlage 16



In order not to overwrite the texmf.cnf and mktex.cnf files of people who are already using Web2c for win32, those files are distributed as texmf.xam and mktex.xam. You must rename them if you don't already have .cnf files.

Configuration

If you have respected the previous layout for the tree, ie the relative position of windvi.exe with respect to the texmf directory, you should not have anything more to configure than update your PATH environment variable.

If you want to use windvi.exe in another context, you may need to set the TEXMFMAIN and / or TEXMFCNF environment variable. TEXMFMAIN must point to the texmf directory and TEXMFCNF to the directory containing texmf.cnf.

Generation of PK files

The generation of PK files is under control of the Kpathsea library through the use of mktexpk.exe. You can choose the destination for generated files — the scheme is explained in detail in the Kpathsea documentation.

The main points are:

- any generated file will go in the same texmf tree as the one in which the font source has been found,
- if the source directory is not writable, the directory named by VARTEXFONTS will be used, so you had better set this variable to something meaningful in texmf.cnf
- □ MT_FEATURES can be set either in mktex.cnf or in your environment to control the naming of generated files: you can add 'dosnames', 'nomode', 'stripsupplier', 'striptypeface', 'fontmaps' and 'varfonts' to the features. Feel free to experiment with them by setting MT_FEATURES in the environment and checking with 'mktexnam cmr10' for the result you want.

Voorjaar 1998

Bijlage 16 Fabrice Popineau

Type1 fonts

In order to use gsftopk.exe to generate PK files for Type I fonts, you will need to install Ghostscript. Ghostscript is used in the background for computing the bitmaps. Setting it up is quite easy; assuming that Ghostscript has been installed in c:\gstools\gs5.10 and fonts in c:\gstools\fonts, add to your environment:

set GS_PATH=c:\gstools\gs5.10\gswin32c.exe
set GS_LIB=c:\gstools\gs5.10;c:\gstools\fonts

After that, Windvi should be able to generate PK files for your Type I fonts, providing you have the corresponding vf and tfm files. It is however wise to try mktexnam.exe on some of your fonts ('mktexnam ptmr8r' for example) to check that the fonts will be put at the right place.

Quick startup

Create a shortcut to Windvi on your desktop:

- click right button on the desktop,
- □ New Shortcut,
- □ browse and find windvi.exe
- п ОК

Next, explore your computer, drag and drop some dvi file onto the Windvi icon. If everything goes well, Windvi will open your dvi file and choose a suitable shrink factor for the page to be fully displayed.

Reference guide

Command line options

- +<page> Specifies the first page to show. If + is given without a number, the last page is assumed; the first page is the default.
- -altfont Declares a default font to use when the font in the dvi file cannot be found. This is useful, for example, with PostScript fonts. Defaults to cmr10
- -background <color> uses ;color; as background color
- -bg <color> same as -background
- -debug <bitmask> If nonzero, prints additional information on standard output. The number is taken as a set of independent bits. The meaning of each bit follows. I=bitmaps; 2=dvi translation; 4=pk reading; 8=batch operation; 16=events; 32=file opening; 64=PostScript communication; 128=Kpathsea stat(2) calls; 256=Kpathsea hash table lookups; 512=Kpathsea path definitions; 1024=Kpathsea path expansion; 2048=Kpathsea searches. To trace everything having to do with file searching and opening, use 4000. Some

- of these debugging options are actually provided by Kpathsea. See the 'Debugging' section in the Kpathsea manual.
- -density <density> Determines the density used when shrinking bitmaps for fonts. A higher value produces a lighter font. The default value is 40. For monochrome displays; for color displays, use -gamma. Same as -S.
- -foreground <color> uses ;color; as foreground color
- -fg <color> same as -foreground
- -gamma <gamma> Controls the interpolation of colors in the greyscale anti-aliasing color palette. Default value is 1.0. For o; gamma; I, the fonts will be lighter (more like the background), and for gamma; I, the fonts will be darker (more like the foreground). Negative values behave the same way, but use a slightly different algorithm. For color and grayscale displays; for monochrome, see -density.
- -hush Causes Windvi to suppress all suppressible warnings.
- -hushchars Causes Windvi to suppress warnings about references to characters which are not defined in the font
- -hushchecksums Causes Windvi to suppress warnings about checksum mismatches between the dvi file and the font file.
- -hushspecials Causes Windvi to suppress warnings about special strings that it cannot process.
- -keep Sets a flag to indicate that Windvi should not move to the home position when moving to a new page.
 See also the 'k' keystroke.
- -margins <dimen> Specifies the size of both the top margin and side margin. This should be a decimal number optionally followed by "cm", e.g., 1.5 or 3cm, giving a measurement in inches or centimeters. It determines the "home" position of the page within the window as follows. If the entire page fits in the window, then the margin settings are ignored. If, even after removing the margins from the left, right, top, and bottom, the page still cannot fit in the window, then the page is put in the window such that the top and left margins are hidden, and presumably the upper left-hand corner of the text on the page will be in the upper left-hand corner of the window. Otherwise, the text is centered in the window. See also -sidemargin, -topmargin, and the keystroke 'M.'
- -mfmode <mode-def>
 Specifies a mode-def string,
 which can be used in searching for fonts. It is also passed to Metafont during automatic creation of fonts.
- -mgs <size> Same as -mgsI.
- -mgs[n < size>] Specifies the size of the window to be used for the "magnifying glass" for Button n . The size may be given as an integer (indicating that the

148 MAPS

Windvi User's Manual Bijlage 16

- magnifying glass is to be square), or it may be given in the form width x height. Defaults are 200x150, 400x250, 700x500, 1000x800, and 1200x1200.
- -nogrey Turns off the use of greyscale anti-aliasing when printing shrunken bitmaps.
- -nomakepk Turns off automatic generation of font files that cannot be found by other means.
- -offsets Specifies the size of both the horizontal and vertical offsets of the output on the page. This should be a decimal number optionally followed by "cm", e.g., I.5 or 3cm, giving a measurement in inches or centimeters. By decree of the Stanford TeX Project, the default TeX page origin is always I inch over and down from the top-left page corner, even when non-American paper sizes are used. Therefore, the default offsets are I.0 inch. See also -xoffset and -yoffset.
- -p <dpi> Defines the size of the fonts to use, in pixels per inch. The default value is 600.
- -qpaper <papertype> Specifies the size of the printed page. This may be of the form widthheight (or widthheightcm), where width is the width in inches (or cm) and height is the height in inches (or cm), respectively. There are also synonyms which may be used: us (8.5x11), usr (11x8.5), legal (8.5x14), foolscap (13.5x17), as well as the ISO sizes a1 a7, b1 b7, c1 c7, a1r a7r (a1 a7rotated), etc. The default size is 21 x 29.7 cm.
- -rv Causes the page to be displayed with white characters on a black background, instead of vice versa.
- -s <shrinkfactor> Defines the initial shrink factor.
 The default value is to choose en appropriate factor.
- -S <density> Same as -density, q.v.
- -sidemargin <dimen> Specifies the side margin (see -margins).
- -topmargin <dimen> Specifies the top and bottom margins (see -margins).
- -xoffset <dimen> Specifies the size of the horizontal offset of the output on the page. See -offsets .
- -yoffset <dimen> Specifies the size of the vertical offset of the output on the page. See -offsets .

Shortcut keys

Home, '~' goto the upper left corner of the page. If margins are active, use them.

Next, 'n', Enter goto next page.

Prior, 'b', Backspace goto previous page.

Ctrl-Home, Ctrl-End goto first (resp. last) page.

Numpad +, Numpad - zoom in (resp. out).

Arrow keys, 'l', 'r', 'u', 'd' move in the corresponding direction (left, right, up, down).

'k' Normally when Windvi switches pages, it moves to the home position as well. The 'k' keystroke toggles a 'keep-position' flag which, when set, will keep the same position when moving between pages.

- 'M' set margins at the cursor.
- 't' change tick units (cursor position).

FAQ

- Windvi opens and closes immediately. You should check your installation:
 - □ did you rename the .xam files into .cnf files ?
 - □ have you .cnf files?
 - □ what mktexnam cmr10 does report?
 - □ in case of trouble, do the following:

set KPATHSEA_DEBUG_OUTPUT=err.log
mkktexnam --debug=1536 cmr10

and send the err.log file to mailto:Fabrice.Popineau@supelec.fr

2. Windvi is stuck with the hour glass cursor, displaying some font name in the status bar. Currently, when kpathsea is generating fonts, Windvi is blocked. You can't see any progress status. This is because kpathsea-based programs are inherently console mode programs and Windvi is a GUI program. If it takes too long time and the status bar doesn't change, there is the chance of an improper installation. Check with the previous question. In this case, you will need to kill Windvi by hand, and any process named mf.exe or mktexpk.exe too.

Known bugs and TODO list

- □ Windvi is uninterruptible during font loading;
- □ The option –version makes Windvi abort;
- □ We need to add the preview of ps inclusions by using Ghostscript:
- □ We need to add more support for 'specials';
- Windvi is resource consuming;
- □ There are probably some other bugs left.

Color naming

You can use 'rgb:/rr/gg/bb/' where rr, gg and bb are the hexadecimal (oo-FF) intensities of red, green and blue component, or any of the predefined symbolic names. ^I

Voorjaar 1998

I. editor's note: the HTML file lists alle of the defined names at this point in the text.