How Cloud Manager uses cloud provider permissions

Cloud Manager

Ben Cammett, Aksel Davis December 07, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm/reference_permissions.html on December 07, 2020. Always check docs.netapp.com for the latest.



Table of Contents

How Cloud Manager uses cloud provider permissions	 1
What Cloud Manager does with AWS permissions	 1
What Cloud Manager does with Azure permissions	 4
What Cloud Manager does with GCP permissions	 8

How Cloud Manager uses cloud provider permissions

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in the policies provided by NetApp. You might want to understand what Cloud Manager does with these permissions.

What Cloud Manager does with AWS permissions

Cloud Manager uses an AWS account to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Security Token Service (STS), and the Key Management Service (KMS).

Actions	Purpose
"ec2:StartInstances", "ec2:StopInstances", "ec2:DescribeInstances", "ec2:DescribeInstanceStatus", "ec2:RunInstances", "ec2:TerminateInstances", "ec2:ModifyInstanceAttribute",	Launches a Cloud Volumes ONTAP instance and stops, starts, and monitors the instance.
"ec2:DescribeInstanceAttribute",	Verifies that enhanced networking is enabled for supported instance types.
"ec2:DescribeRouteTables", "ec2:DescribeImages",	Launches a Cloud Volumes ONTAP HA configuration.
"ec2:CreateTags",	Tags every resource that Cloud Manager creates with the "WorkingEnvironment" and "WorkingEnvironmentId" tags. Cloud Manager uses these tags for maintenance and cost allocation.
"ec2:CreateVolume", "ec2:DescribeVolumes", "ec2:ModifyVolumeAttribute", "ec2:AttachVolume", "ec2:DeleteVolume", "ec2:DetachVolume",	Manages the EBS volumes that Cloud Volumes ONTAP uses as back-end storage.

Actions	Purpose
"ec2:CreateSecurityGroup", "ec2:DeleteSecurityGroup", "ec2:DescribeSecurityGroups", "ec2:RevokeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupIngress", "ec2:RevokeSecurityGroupIngress",	Creates predefined security groups for Cloud Volumes ONTAP.
"ec2:CreateNetworkInterface", "ec2:DescribeNetworkInterfaces", "ec2:DeleteNetworkInterface", "ec2:ModifyNetworkInterfaceAttribute",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"ec2:DescribeSubnets", "ec2:DescribeVpcs",	Gets the list of destination subnets and security groups, which is needed when creating a new working environment for Cloud Volumes ONTAP.
"ec2:DescribeDhcpOptions",	Determines DNS servers and the default domain name when launching Cloud Volumes ONTAP instances.
"ec2:CreateSnapshot", "ec2:DeleteSnapshot", "ec2:DescribeSnapshots",	Takes snapshots of EBS volumes during initial setup and whenever a Cloud Volumes ONTAP instance is stopped.
"ec2:GetConsoleOutput",	Captures the Cloud Volumes ONTAP console, which is attached to AutoSupport messages.
"ec2:DescribeKeyPairs",	Obtains the list of available key pairs when launching instances.
"ec2:DescribeRegions",	Gets a list of available AWS regions.
"ec2:DeleteTags", "ec2:DescribeTags",	Manages tags for resources associated with Cloud Volumes ONTAP instances.
"cloudformation:CreateStack", "cloudformation:DeleteStack", "cloudformation:DescribeStacks", "cloudformation:DescribeStackEvents", "cloudformation:ValidateTemplate",	Launches Cloud Volumes ONTAP instances.

Actions	Purpose
"iam:PassRole", "iam:CreateRole", "iam:DeleteRole", "iam:PutRolePolicy", "iam:CreateInstanceProfile", "iam:DeleteRolePolicy", "iam:AddRoleToInstanceProfile", "iam:RemoveRoleFromInstanceProfile", "iam:DeleteInstanceProfile",	Launches a Cloud Volumes ONTAP HA configuration.
"iam:ListInstanceProfiles", "sts:DecodeAuthorizationMessage", "ec2:AssociateIamInstanceProfile", "ec2:DescribeIamInstanceProfileAssociations", "ec2:DisassociateIamInstanceProfile",	Manages instance profiles for Cloud Volumes ONTAP instances.
"s3:GetBucketTagging", "s3:GetBucketLocation", "s3:ListAllMyBuckets", "s3:ListBucket"	Obtains information about AWS S3 buckets so Cloud Manager can integrate with the NetApp Data Fabric Cloud Sync service.
"s3:CreateBucket", "s3:DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Manages the S3 bucket that a Cloud Volumes ONTAP system uses as a capacity tier for data tiering.
"kms:List*", "kms:ReEncrypt*", "kms:Describe*", "kms:CreateGrant",	Enables data encryption of Cloud Volumes ONTAP using the AWS Key Management Service (KMS).
"ce:GetReservationUtilization", "ce:GetDimensionValues", "ce:GetCostAndUsage", "ce:GetTags"	Obtains AWS cost data for Cloud Volumes ONTAP.

Actions	Purpose
"ec2:CreatePlacementGroup", "ec2:DeletePlacementGroup"	When you deploy an HA configuration in a single AWS Availability Zone, Cloud Manager launches the two HA nodes and the mediator in an AWS spread placement group.
"ec2:DescribeReservedInstancesOfferings"	Cloud Manager uses the permission as part of Cloud Compliance deployment to choose which instance type to use.
"s3:DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetObject", "s3:ListBucket", "s3:ListAllMyBuckets", "s3:GetBucketTagging", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:GetBucketPublicAccessBlock"	Cloud Manager uses these permissions when you enable the Backup to S3 service.

What Cloud Manager does with Azure permissions

The Cloud Manager Azure policy includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP in Azure.

Actions	Purpose
"Microsoft.Compute/locations/operations/read", "Microsoft.Compute/locations/vmSizes/read", "Microsoft.Compute/operations/read", "Microsoft.Compute/virtualMachines/instanceVie w/read", "Microsoft.Compute/virtualMachines/powerOff/ac tion", "Microsoft.Compute/virtualMachines/read", "Microsoft.Compute/virtualMachines/restart/actio n", "Microsoft.Compute/virtualMachines/start/action", "Microsoft.Compute/virtualMachines/deallocate/ac tion", "Microsoft.Compute/virtualMachines/deallocate/ac tion", "Microsoft.Compute/virtualMachines/wmSizes/rea d", "Microsoft.Compute/virtualMachines/write",	Creates Cloud Volumes ONTAP and stops, starts, deletes, and obtains the status of the system.
"Microsoft.Compute/images/write", "Microsoft.Compute/images/read",	Enables Cloud Volumes ONTAP deployment from a VHD.
"Microsoft.Compute/disks/delete", "Microsoft.Compute/disks/read", "Microsoft.Storage/checknameavailability/read", "Microsoft.Storage/operations/read", "Microsoft.Storage/storageAccounts/listkeys/action ", "Microsoft.Storage/storageAccounts/read", "Microsoft.Storage/storageAccounts/regeneratekey/action", "Microsoft.Storage/storageAccounts/write" "Microsoft.Storage/storageAccounts/write" "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/usages/read",	Manages Azure storage accounts and disks, and attaches the disks to Cloud Volumes ONTAP.
"Microsoft.Network/networkInterfaces/read", "Microsoft.Network/networkInterfaces/write", "Microsoft.Network/networkInterfaces/join/action ",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"Microsoft.Network/networkSecurityGroups/read" , "Microsoft.Network/networkSecurityGroups/write ", "Microsoft.Network/networkSecurityGroups/join/a ction",	Creates predefined network security groups for Cloud Volumes ONTAP.

Actions	Purpose
"Microsoft.Resources/subscriptions/locations/read", "Microsoft.Network/locations/operationResults/re ad", "Microsoft.Network/locations/operations/read", "Microsoft.Network/virtualNetworks/read", "Microsoft.Network/virtualNetworks/checkIpAddr essAvailability/read", "Microsoft.Network/virtualNetworks/subnets/read ", "Microsoft.Network/virtualNetworks/subnets/virtu alMachines/read", "Microsoft.Network/virtualNetworks/virtualMachi nes/read", "Microsoft.Network/virtualNetworks/virtualMachi nes/read", "Microsoft.Network/virtualNetworks/subnets/join/ action",	Gets network information about regions, the target VNet and subnet, and adds Cloud Volumes ONTAP to VNets.
"Microsoft.Network/virtualNetworks/subnets/write", "Microsoft.Network/routeTables/join/action",	Enables VNet service endpoints for data tiering.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write",	Deploys Cloud Volumes ONTAP from a template.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write", "Microsoft.Resources/resources/read", "Microsoft.Resources/subscriptions/operationresults/read", "Microsoft.Resources/subscriptions/resourceGroups/delete", "Microsoft.Resources/subscriptions/resourceGroups/read", "Microsoft.Resources/subscriptions/resourcegroups/resources/read", "Microsoft.Resources/subscriptions/resourcegroups/resources/read", "Microsoft.Resources/subscriptions/resourceGroups/write",	Creates and manages resource groups for Cloud Volumes ONTAP.
"Microsoft.Compute/snapshots/write", "Microsoft.Compute/snapshots/read", "Microsoft.Compute/disks/beginGetAccess/action"	Creates and manages Azure managed snapshots.

Actions	Purpose
"Microsoft.Compute/availabilitySets/write", "Microsoft.Compute/availabilitySets/read",	Creates and manages availability sets for Cloud Volumes ONTAP.
"Microsoft.MarketplaceOrdering/offertypes/publis hers/offers/plans/agreements/read", "Microsoft.MarketplaceOrdering/offertypes/publis hers/offers/plans/agreements/write"	Enables programmatic deployments from the Azure Marketplace.
"Microsoft.Network/loadBalancers/read", "Microsoft.Network/loadBalancers/delete", "Microsoft.Network/loadBalancers/backendAddre ssPools/read", "Microsoft.Network/loadBalancers/backendAddre ssPools/join/action", "Microsoft.Network/loadBalancers/frontendIPConf igurations/read", "Microsoft.Network/loadBalancers/loadBalancing Rules/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/join/action", "Microsoft.Network/loadBalancers/probes/join/action", "Microsoft.Network/loadBalancers/probes/join/action",	Manages an Azure load balancer for HA pairs. Enables management of locks on Azure disks.
"Microsoft.Authorization/roleDefinitions/write", "Microsoft.Authorization/roleAssignments/write", "Microsoft.Web/sites/*"	Manages failover for HA pairs.
"Microsoft.Network/privateEndpoints/write", "Microsoft.Storage/storageAccounts/PrivateEndpoi ntConnectionsApproval/action", "Microsoft.Storage/storageAccounts/privateEndpoi ntConnections/read", "Microsoft.Network/privateEndpoints/read", "Microsoft.Network/privateDnsZones/write", "Microsoft.Network/privateDnsZones/virtualNetw orkLinks/write", "Microsoft.Network/virtualNetworks/join/action", "Microsoft.Network/privateDnsZones/A/write", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/virtualNetw orkLinks/read",	isn't provided to outside the subnet. Cloud
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",	Enables Cloud Manager to delete volumes for Azure NetApp Files.

Actions	Purpose
"Microsoft.Resources/deployments/operationStatu ses/read"	Azure requires this permission for some virtual machine deployments (it depends on the underlying physical hardware that's used during deployment).
"Microsoft.Resources/deployments/operationStatu ses/read", "Microsoft.Insights/Metrics/Read", "Microsoft.Compute/virtualMachines/extensions/write", "Microsoft.Compute/virtualMachines/extensions/read", "Microsoft.Compute/virtualMachines/extensions/delete", "Microsoft.Compute/virtualMachines/delete", "Microsoft.Network/networkInterfaces/delete", "Microsoft.Network/networkSecurityGroups/delete", "Microsoft.Resources/deployments/delete",	Enables you to use Global File Cache.
"Microsoft.Compute/diskEncryptionSets/read"	Enables Cloud Manager to encrypt Azure managed disks on single node Cloud Volumes ONTAP systems using external keys from another account. This feature is supported using APIs.

What Cloud Manager does with GCP permissions

The Cloud Manager policy for GCP includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP.

Actions	Purpose
 compute.disks.create compute.disks.createSnapshot compute.disks.delete compute.disks.get compute.disks.list compute.disks.setLabels compute.disks.use 	To create and manage disks for Cloud Volumes ONTAP.
compute.firewalls.createcompute.firewalls.deletecompute.firewalls.getcompute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.

Actions	Purpose
- compute.globalOperations.get	To get the status of operations.
compute.images.getcompute.images.getFromFamilycompute.images.listcompute.images.useReadOnly	To get images for VM instances.
compute.instances.attachDiskcompute.instances.detachDisk	To attach and detach disks to Cloud Volumes ONTAP.
- compute.instances.create - compute.instances.delete	To create and delete Cloud Volumes ONTAP VM instances.
- compute.instances.get	To list VM instances.
- compute.instances.getSerialPortOutput	To get console logs.
- compute.instances.list	To retrieve the list of instances in a zone.
- compute.instances.setDeletionProtection	To set deletion protection on the instance.
- compute.instances.setLabels	To add labels.
- compute.instances.setMachineType	To change the machine type for Cloud Volumes ONTAP.
- compute.instances.setMetadata	To add metadata.
- compute.instances.setTags	To add tags for firewall rules.
compute.instances.startcompute.instances.stopcompute.instances.updateDisplayDevice	To start and stop Cloud Volumes ONTAP.
- compute.machineTypes.get	To get the numbers of cores to check qoutas.
- compute.projects.get	To support multi-projects.
compute.snapshots.createcompute.snapshots.deletecompute.snapshots.getcompute.snapshots.listcompute.snapshots.setLabels	To create and manage persistent disk snapshots.
 compute.networks.get compute.regions.get compute.regions.list compute.subnetworks.get compute.subnetworks.list compute.zoneOperations.get compute.zones.get compute.zones.list 	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.

Actions	Purpose
- deploymentmanager.compositeTypes.get - deploymentmanager.deployments.create - deploymentmanager.deployments.delete - deploymentmanager.deployments.get - deploymentmanager.deployments.list - deploymentmanager.manifests.get - deploymentmanager.manifests.list - deploymentmanager.operations.get - deploymentmanager.operations.list - deploymentmanager.resources.get - deploymentmanager.resources.list - deploymentmanager.typeProviders.get - deploymentmanager.typeProviders.list - deploymentmanager.typeProviders.list - deploymentmanager.types.get - deploymentmanager.types.get	To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.
logging.logEntries.listlogging.privateLogEntries.list	To get stack log drives.
- resourcemanager.projects.get	To support multi-projects.
 storage.buckets.create storage.buckets.delete storage.buckets.get storage.buckets.list storage.buckets.update 	To create and manage a Google Cloud Storage bucket for data tiering.
- cloudkms.cryptoKeyVersions.useToEncrypt- cloudkms.cryptoKeys.get- cloudkms.cryptoKeys.list- cloudkms.keyRings.list	To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.
- compute.instances.setServiceAccount - iam.serviceAccounts.actAs - iam.serviceAccounts.getIamPolicy - iam.serviceAccounts.list - storage.objects.get - storage.objects.list	To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.
 compute.addresses.list compute.backendServices.create compute.networks.updatePolicy compute.regionBackendServices.create compute.regionBackendServices.get compute.regionBackendServices.list 	To deploy HA pairs.

Copyright Information

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval systemwithout prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.