Part II - Assemblers

In this part you will play the role of the assembler and assign a location counter (LC) value and a program counter (PC) for each instruction. In addition, you will actually assemble the given MIPS instructions by filling in the fields like the example provided in gray. This process will be reversed from what you implemented within Part I.

- 1. Provide the integer values for each of the fields in each MIPS instruction
- 2. Convert those integer values to their binary equivalent (32-bits)
- 3. Convert the 32-bit string to the hex value equivalent.

LC		addi	\$v0	\$zero	0		PC			
		8	2	0	0					
001000 00000 00010 00000000000000										
0			4							
	next:	lw	\$t9	0	(\$a0)					
		35	25	0	4					
100011 00100 11001 00000000000000										
4			8							
		addi	\$v0	\$v0	1					
		8	2	2	1					
001000 00010 00010 00000000000001										
8			12							
		sw	\$t9	\$0	(\$a1)					
		43	25	0	5					
101011 00101 11001 0000000000000										
12			16							
LC							PC			
		addi	\$a0	\$a0	4					
		8	4	4	4					
001000 00100 00100 0000000000000000										

16		20840004						
		addi	\$a1	\$a1	4			
		8	5	5	4			
		00100	0 00101 001	01 00000000	00000100			
20		20A50004						
		bne	\$t9	\$zero	next			
		5	25	0	-6			
		00010	1 00000 110	01 11111111	111111010			
24	24 1419FFFA							
		jr	\$ra					
		8	31					
	00	0000 11111	0000000000	00000 0010	00			
28		03E00008						