The geometry package

Hideo Umeki and David Carlisle

The geometry package

This package provides a flexible and easy interface to page dimensions. You can change the page layout with intuitive parameters. For instance, if you want to set a margin to 2cm from each edge of the paper, you can type just \usepackage[margin=2cm] {geometry}. The page layout can be changed in the middle of the document with \newgeometry command.

Package *geometry* is copyrighted by Hideo Umeki and David Carlisle and is licenced under LATEX Project Public License.

Introduction

To set dimensions for page layout in LATEX is not straightforward. You need to adjust several LATEX native dimensions to place a text area where you want. If you want to center the text area in the paper you use, for example, you have to specify native dimensions as follows:

Without package *calc*, the above example would need more tedious settings. Package *geometry* provides an easy way to set page layout parameters. In this case, what you have to do is just

```
\usepackage[text={7in,10in},centering]{geometry}
```

Besides centering problem, setting margins from each edge of the paper is also troublesome. But *geometry* also make it easy. If you want to set each margin to 1.5in, you can type

```
\usepackage[margin=1.5in]{geometry}
```

Thus, the geometry package has an auto-completion mechanism, in which un-

specified dimensions are automatically determined. The *geometry* package will be also useful when you have to set page layout obeying the following strict instructions: for example,

The total allowable width of the text area is 6.5 inches wide by 8.75 inches high. The top margin on each page should be 1.2 inches from the top edge of the page. The left margin should be 0.9 inch from the left edge. The footer with page number should be at the bottom of the text area.

In this case, using geometry you can type

Setting a text area on the paper in document preparation system has some analogy to placing a window on the background in the window system. The name *geometry* comes from the -geometry option used for specifying a size and location of a window in X Window System.

Page geometry

Figure 1 shows the page layout dimensions defined in the *geometry* package. The page layout contains a *total body* (printable area) and *margins*. The *total body* consists of a *body* (text area) with an optional *header*, *footer* and marginal notes (*marginpar*). There are four margins: *left*, *right*, *top* and *bottom*. For twosided documents, horizontal margins should be called *inner* and *outer*.

paper : total body and margins

total body : body (text area) (optional head, foot and marginpar)

margins : left (inner), right (outer), top and bottom

Each margin is measured from the corresponding edge of a paper. For example, left margin (inner margin) means a horizontal distance between the left (inner) edge of the paper and that of the total body. Therefore the left and top margins defined in *geometry* are different from the native dimensions \leftmargin and \topmargin. The size of a *body* (text area) can be modified by \textwidth and \textheight.

The dimensions for paper, total body and margins have the following relations.

$$paperwidth = left + width + right \tag{1}$$

$$paperheight = top + height + bottom$$
 (2)




Figure 1. Dimension names used in the *geometry* package. Width = textwidth and height = textheight by default. Left, right, top and bottom are margins. If margins on verso pages are swapped by twoside option, margins specified by left and right options are used for the inside and outside margins respectively. Inner and outer are aliases of left and right respectively.

The total body *width* and *height* would be defined:

$$width := textwidth \quad (+ marginparsep + marginparwidth)$$
 (3)

$$height := textheight \quad (+ headheight + headsep + footskip)$$
 (4)

In Equation (3) width := textwidth by default, while marginparsep and margin-parwidth are included in width if includemp option is set true. In Equation (4), height := textheight by default. If includehead is set to true, headheight and headsep are considered as a part of height. In the same way, includefoot takes footskip into height. Figure 2 shows how these options work in the vertical direction.




Figure 2. *Includehead* and *includefoot* include the head and foot respectively into *total body*. (a) *height* = *textheight* (default). (b) *height* = *textheight* + *headheight* + *headsep* + *footskip* if *includehead* and *includefoot*. If the top and bottom margins are specified, *includehead* and *includefoot* result in shorter *textheight*.

Thus, the page layout consists of three parts (lengths) in each direction: one body and two margins. If the two of them are explicitly specified, the other length is obvious and no need to be specified. Figure 3 shows a simple model of page dimensions. When a length L is given and is partitioned into the body b, the margins a and c, it's obvious that

$$L = a + b + c \tag{5}$$

The specification with two of the three (a, b and c) fixed explicitly is solvable. If two or more are left unspecified or "underspecified", Equation (5) cannot be solved without any other relation between them. If all of them are specified, then it needs to check whether or not they satisfy Equation (5), that is too much specification or "overspecified".




Figure 3. A simple model of page dimensions.

The *geometry* package has auto-completion mechanism that saves the trouble of specifying the page layout dimensions. For example, you can set

\usepackage[width=14cm, left=3cm]{geometry}

on A4 paper. In this case you don't have to set the right margin. The details of auto-completion will be described in Section 6.

User interface

Commands

The *geometry* package provides the following commands:

- \geometry{\langle options \rangle}
- \newgeometry{\langle options \range \} and \restoregeometry
- \savegeometry{ $\langle name \rangle$ } and \loadgeometry{ $\langle name \rangle$ }

 $\glue{geometry}{\langle options \rangle}$ changes the page layout according to the options specified in the argument. This command, if any, should be placed only in the preamble (before $\glue{geometry}$).

The *geometry* package may be used as part of a class or another package you use in your document. The command \geometry can overwrite some of the settings in the preamble. Multiple use of \geometry is allowed and then processed with the options concatenated. If *geometry* is not yet loaded, you can use only \usepackage[\langle options \rangle] \{geometry\} instead of \geometry.

\newgeometry{\langle options\rangle} changes the page layout mid-document. The command \newgeometry is almost similar to \geometry except that \newgeometry disables all the options specified by \usepackage and \geometry in the preamble and skips papersize-related options.

\restoregeometry restores the page layout specified in the preamble. This command has no arguments. See Section 7 for details.

\savegeometry{ $\langle name \rangle$ } saves the page dimensions as $\langle name \rangle$ where you put this command.

\loadgeometry{ $\langle name \rangle$ } loads the page dimensions saved as $\langle name \rangle$. See Section 7 for details.

Optional argument

The *geometry* package adopts *keyval* interface $\langle key \rangle = \langle value \rangle$ for the optional argument to \usepackage, \geometry and \newgeometry.

The argument includes a list of comma-separated *keyval* options and has basic rules as follows:

- Multiple lines are allowed, while blank lines are not.
- Any spaces between words are ignored.
- Options are basically order-independent.

(There are some exceptions. See Section 6 for details.)

For example,

is equivalent to

```
\usepackage[height=10in,a5paper,hmargin={3cm,0.8in}]{geometry}
```

Some options are allowed to have sub-list, e.g. $\{3cm, 0.8in\}$. Note that the order of values in the sub-list is significant. The above setting is also equivalent to the followings:

```
\usepackage{geometry}
\geometry{height=10in,a5paper,hmargin={3cm,0.8in}}
or
\usepackage[a5paper]{geometry}
\geometry{hmargin={3cm,0.8in},height=8in}
\geometry{height=10in}
```

Thus, multiple use of \geometry just appends options.

The geometry package supports package calc. For example,

```
\usepackage{calc}
\usepackage[textheight=20\baselineskip+10pt]{geometry}
```

Option types

The *geometry* options are categorized into four types:

Boolean type takes a boolean value (*true* or *false*). If no value, *true* is set by default:

```
\langle key \rangle = true | false \langle key \rangle with no value is equivalent to \langle key \rangle = true.
```

Examples:

verbose=true, includehead, twoside=false

Paper name is the exception. The preferred paper name should be set with no values. Whatever value is given, it is ignored. For instance, a4paper=XXX is equivalent to a4paper.

Single-valued type takes a mandatory value:

```
\langle key \rangle = \langle value \rangle
```

Examples:

width=7in, left=1.25in, footskip=1cm, height=.86\paperheight

Double-valued type takes a pair of comma-separated values in braces. The two values can be shortened to one value if they are identical:

```
\begin{split} &\langle key\rangle = \{\langle value1\rangle \text{, } \langle value2\rangle \} \\ &\langle key\rangle = \langle value\rangle \text{ is equivalent to } \langle key\rangle = \{\langle value\rangle, \langle value\rangle \}. \end{split}
```

Examples:

 $hmargin={1.5in,1in}, scale=0.8, body={7in,10in}$

Triple-valued type takes three mandatory, comma-separated values in braces:

$$\langle key \rangle = \{\langle value1 \rangle, \langle value2 \rangle, \langle value3 \rangle \}$$

Each value must be a dimension or null. When you give an empty value or *, it means null and leaves the appropriate value to the autocompletion mechanism. You need to specify at least one dimension, typically two dimensions. You can set nulls for all the values, but it makes no sense.

Examples:

```
hdivide={2cm,*,1cm}, vdivide={3cm,19cm, }, divide={1in,*,1in}
```

Option details

This section describes all options available in *geometry*. Paper size, drivers and "other options" are not available as arguments of \newgeometry (See Section 7).

Paper size

The options below set paper/media size and orientation.

paper | papername specifies the paper size by name:

```
paper=\langle paper-name\rangle
```

For convenience, you can specify the paper name without paper=. For example, a4paper is equivalent to paper=a4paper.

⟨paper-name⟩ specifies paper name. The value part is ignored even if any. For example, the followings have the same effect: a5paper, a5paper=true, a5paper=false and so forth.

a [0-6] paper, b [0-6] paper and c [0-6] paper are ISO A, B and C series of paper sizes respectively.

The JIS (Japanese Industrial Standards) A-series is identical to the ISO A-series, but the JIS B-series is different from the ISO B-series. b[0-6]j should be used for the JIS B-series.

⟨*paper-name*⟩ may be one of:

a0paper, a1paper, a2paper, a3paper, a4paper, a5paper, a6paper, b0paper, b1paper, b2paper, b3paper, b4paper, b5paper, b6paper, c0paper, c1paper, c2paper, c3paper, c4paper, c5paper, c6paper, b0j, b1j, b2j, b3j, b4j, b5j, b6j, ansiapaper, ansibpaper, ansicpaper, ansidpaper, ansiepaper, letterpaper, executivepaper, or legalpaper.

screen a special paper size with (W,H) = (225 mm, 180 mm). For presentation with PC and video projector, screen, centering with slide documentclass would be useful.

paperwidth width of the paper:

```
paperwidth=\langle length \rangle
```

paperheight height of the paper:

```
paperheight=\langle length \rangle
```

papersize width and height of the paper:

```
papersize=\{\langle width \rangle, \langle height \rangle\} or papersize=\langle length \rangle
```

landscape switches the paper orientation to landscape mode.

portrait switches the paper orientation to portrait mode. This is equivalent to landscape=false.

The options for paper names (e.g., a4paper) and orientation (portrait and landscape) can be set as document class options. For example, you can set \documentclass[a4paper,landscape]{article}, then a4paper and landscape are processed in *geometry* as well. This is also the case for twoside and twocolumn (see also Section 5).

Layout size

You can specify the layout area with options described in this section regardless of the paper size. The options would help to print the specified layout to a different sized paper. For example, with a4paper and layout=a5paper, the package uses A5 layout to calculate margins on A4 paper. The layout size

defaults to the same as the paper. The options for the layout size are available in \newgeometry, so that you can change the layout size in the middle of the document. The paper size itself can't be changed though. Figure 4 shows what the difference between *layout* and *paper* is.




Figure 4. The dimensions related to the layout size. Note that the layout size defaults to the same size as the paper, so you don't have to specify layout-related options explicitly in most cases.

layout specifies the layout size by paper name:

layout=\(paper-name\)

All the paper names defined in *geometry* are available. See Section 5 for details.

layoutwidth width of the layout:

layoutwidth= $\langle length \rangle$

layoutheight height of the layout:

layoutheight= $\langle length \rangle$

layoutsize width and height of the layout:

 $layoutsize=\{\langle width \rangle, \langle height \rangle\} \text{ or } layoutsize=\langle length \rangle$

layouthoffset specifies the horizontal offset from the left edge of the paper:

```
layouthoffset=\langle length\rangle
```

layoutvoffset specifies the vertical offset from the top edge of the paper:

```
layoutvoffset = \langle length \rangle
```

layoutoffset specifies both horizontal and vertical offsets:

```
layoutoffset=\{\langle hoffset \rangle, \langle voffset \rangle\} \text{ or } layoutsize=\langle length \rangle
```

Body size

The options specifying the size of *total body* are described in this section.

hscale ratio of width of total body to \paperwidth.

 $\label{eq:hscale} \verb| hscale=| \langle h\text{-}scale \rangle, e.g., \verb| hscale=| 0.8 | is equivalent to width=| 0.8 \rangle | paperwidth. \\ (0.7 by default)$

vscale ratio of height of *total body* to \paperheight, e.g., vscale= $\langle v\text{-}scale \rangle$ (0.7 by default). vscale=0.9 is equivalent to height=0.9\paperheight.

scale ratio of total body to the paper:

```
scale = \{\langle h\text{-}scale \rangle, \langle v\text{-}scale \rangle\} \text{ or } scale = \langle scale \rangle. (0.7 \text{ by default})
```

width | totalwidth width of total body.

```
width=\langle length \rangle or totalwidth=\langle length \rangle.
```

This dimension defaults to textwidth, but if includemp is set to true, $width \ge textwidth$ because width includes the width of the marginal notes. If textwidth and width are specified at the same time, textwidth takes priority over width.

height | totalheight height of *total body*, excluding header and footer by default. If *includehead* or *includefoot* is set, *height* includes the head or foot of the page as well as *textheight*:

```
height=\langle length \rangle or totalheight=\langle length \rangle
```

If both *textheight* and *height* are specified, *height* will be ignored.

total width and height of total body:

```
total=\langle width \rangle, \langle height \rangle or total=\langle length \rangle
```

textwidth specifies *textwidth*, the width of *body* (the text area):

```
textwidth=\langle length \rangle
```

textheight specifies *textheight*, the height of *body* (the text area):

```
textheight=\langle length \rangle
```

text | body specifies both textwidth and textheight of the body of page:

```
body=\{\langle width \rangle, \langle height \rangle\} or text=\langle length \rangle
```

lines enables users to specify *textheight* by the number of lines:

```
lines = \langle integer \rangle
```

- includehead includes the head of the page, headheight and headsep, into total body. It is set to false by default. It is opposite to ignorehead. See Figure 2 and Figure 5.
- includefoot includes the foot of the page, *footskip*, into *total body*. It is opposite to ignorefoot. It is *false* by default. See Figure 2 and Figure 5.
- includeheadfoot sets both *includehead* and *includefoot* to *true*, which is opposite to ignoreheadfoot. See Figure 2 and Figure 5.
- includemp includes the margin notes, *marginparwidth* and *marginparsep*, into *body* when calculating horizontal calculation.
- includeall sets both *includeheadfoot* and *includemp* to *true*. See Figure 5.
- ignorehead disregards the head of the page, headheight and headsep, in determining vertical layout, but does not change those lengths. It is equivalent to includehead=false. It is set to true by default. See also includehead.
- ignorefoot disregards the foot of page, *footskip*, in determining vertical layout, but does not change that length. This option defaults to *true*. See also includefoot.
- ignoreheadfoot sets both *ignorehead* and *ignorefoot* to *true*. See also includeheadfoot.

ignoremp disregards the marginal notes in determining the horizontal margins (defaults to *true*). If marginal notes overrun the page, the warning message will be displayed when verbose=true. See also includemp and Figure 5.

ignoreall sets both *ignoreheadfoot* and *ignoremp* to *true*. See also includeall.

heightrounded This option rounds *textheight* to *n*-times (where *n* is an integer) of *baselineskip* plus *topskip* to avoid "underfull vbox" in some cases. For example, if *textheight* is 486pt with baselineskip 12pt and topskip 10pt, then

$$\underbrace{478 \text{pt}}_{39 \times 12 \text{pt} + 10 \text{pt}} \ < \ 486 \text{pt} \ < \underbrace{490 \text{pt}}_{40 \times 12 \text{pt} + 10 \text{pt}}$$

as a result *textheight* is rounded to 490pt. heightrounded=false by default.

Figure 5 illustrates various layouts with different layout modes. The dimensions for a header and a footer can be controlled by *nohead* or *nofoot* mode, which sets each length to 0pt directly. On the other hand, options with the prefix ignore do *not* change the corresponding native dimensions.

The following options can specify body and margins simultaneously with three comma-separated values in braces.

hdivide horizontal partitions (left,width,right):

$$hdivide=\{\langle left\ margin \rangle, \langle width \rangle, \langle right\ margin \rangle\}$$

Note that you should not specify all of the three parameters. The best way of using this option is to specify two of three and leave the rest with null (nothing) or *. For example, when you set hdivide={2cm,15cm,}, the margin from the right-side edge of page will be determined calculating paperwidth-2cm-15cm.

vdivide vertical partitions (top,height,bottom):

$$\verb|vdivide={\langle top \ margin \rangle, \langle height \rangle, \langle bottom \ margin \rangle}|$$

divide divide= $\{A,B,C\}$ is interpreted as hdivide= $\{A,B,C\}$ and vdivide= $\{A,B,C\}$.




Figure 5. Sample layouts for total body with different switches: (a) includeheadfoot, (b) includeall, (c) includefoot and (d) includefoot,includemp. If reversemp is set to true, the location of the marginal notes are swapped on every page. Option twoside swaps both margins and marginal notes on verso pages. Note that the marginal note, if any, is printed despite ignoremp or includemp = false and overrun the page in some cases.

Margin size

The options specifying the size of the margins are listed below.

left | lmargin | inner left margin (for oneside) or inner margin (for twoside) of total body. In other words, the distance between the left (inner) edge of the paper and that of total body:

```
left=\langle length \rangle
```

inner has no special meaning, just an alias of left and lmargin.

right | rmargin | outer right or outer margin of total body:

```
right=\length\rangle
```

top | tmargin top margin of the page:

$$top=\langle length \rangle$$

Note this option has nothing to do with the native dimension \topmargin.

bottom | bmargin bottom margin of the page:

```
bottom=\langth\rangle
```

hmargin left and right margin:

```
\verb|hmargin={\langle \textit{left margin} \rangle, \langle \textit{right margin} \rangle}| \text{ or } \verb|hmargin={\langle \textit{length} \rangle}|.
```

vmargin top and bottom margin:

```
vmargin=\{\langle top\ margin \rangle, \langle bottom\ margin \rangle\}\ or\ vmargin=\langle length \rangle
```

margin margin= $\{A,B\}$ is equivalent to hmargin= $\{A,B\}$ and vmargin= $\{A,B\}$. margin=A is automatically expanded to hmargin=A and vmargin=A.

hmarginratio horizontal margin ratio of *left* (inner) to *right* (outer). The value of $\langle ratio \rangle$ should be specified with colon-separated two values. Each value should be a positive integer less than 100 to prevent arithmetic overflow, e.g., 2:3 instead of 1:1.5. The default ratio is 1:1 for *oneside*, 2:3 for *twoside*.

 ${\tt vmarginratio}\ \ {\tt vertical}\ {\tt margin}\ {\tt ratio}\ {\tt of}\ {\it top}\ {\tt to}\ {\it bottom}.\ {\tt The}\ {\tt default}\ {\tt ratio}\ {\tt is}\ 2:3.$

marginratio | ratio horizontal and vertical margin ratios:

 ${\tt marginratio=} \{\langle \textit{horizontal ratio} \rangle, \langle \textit{vertical ratio} \rangle \} \text{ or } {\tt marginratio=} \langle \textit{ratio} \rangle$

- hcentering sets auto-centering horizontally and is equivalent to hmarginratio=1:1. It is set to *true* by default for *oneside*. See also hmarginratio.
- vcentering sets auto-centering vertically and is equivalent to vmarginratio=1:1. The default is *false*. See also vmarginratio.
- centering sets auto-centering and is equivalent to marginratio=1:1. See also marginratio. The default is *false*. See also marginratio.
- twoside switches on twoside mode with left and right margins swapped on verso pages. The option sets \Otwoside and \Omparswitch switches. See also asymmetric.
- asymmetric implements a twosided layout in which margins are not swapped on alternate pages (by setting *oddsidemargin* to *evensidemargin* + *bindingoffset*) and in which the marginal notes stay always on the same side. This option can be used as an alternative to the twoside option. See also *twoside*.
- bindingoffset removes a specified space from the lefthand-side of the page for *oneside* or the inner-side for *twoside*:

bindingoffset= $\langle length \rangle$

This is useful if pages are bound by a press binding (glued, stitched, stapled ...). See Figure 6.

hdivide See description in Section 5.

vdivide See description in Section 5.

divide See description in Section 5.

Native dimensions

The options below overwrite LATEX native dimensions and switches for page layout (See the right-hand side in Figure 1).

b) even (back) pages for twoside a) every page for oneside or odd pages for twoside paper paper total body total body right left outer inner (inner) (outer) (right) (left) bindingoffset bindingoffset

Figure 6. The option *bindingoffset* adds the specified length to the inner margin. Note that *twoside* option swaps the horizontal margins and the marginal notes together with *bindingoffset* on even pages (see b)), but *asymmetric* option suppresses the swap of the margins and marginal notes (but *bindingoffset* is still swapped).

headheight | head modifies headheight, height of header:

 $headheight = \langle length \rangle$ or $head = \langle length \rangle$

headsep modifies *headsep*, separation between header and text (body):

 $headsep=\langle length \rangle$

footskip | foot modifies *footskip*, distance separation between baseline of last line of text and baseline of footer:

 $footskip=\langle length \rangle \text{ or } foot=\langle length \rangle$

nohead eliminates spaces for the head of the page, which is equivalent to both headheight=Opt and headsep=Opt.

nofoot eliminates spaces for the foot of the page, which is equivalent to footskip=0pt.

noheadfoot equivalent to nohead and nofoot, which means that *headheight*, *headsep* and *footskip* are all set to 0pt.

- footnotesep changes the dimension *skipfootins*, separation between the bottom of text body and the top of footnote text.
- marginparwidth | marginpar modifies marginparwidth, width of the marginal notes:

```
marginparwidth=\langle length \rangle
```

marginparsep modifies marginparsep, separation between body and marginal notes:

```
marginparsep=\langle length \rangle
```

- nomarginpar shrinks spaces for marginal notes to 0pt, which is equivalent to marginparwidth=0pt and marginparsep=0pt.
- columnsep modifies *columnsep*, the separation between two columns in *twocolumn* mode.

hoffset modifies hoffset:

```
hoffset=\langle length \rangle
```

voffset modifies voffset:

$$voffset=\langle length \rangle$$

offset horizontal and vertical offset:

```
offset=\{\langle hoffset \rangle, \langle voffset \rangle\} or offset=\langle length \rangle
```

- twocolumn sets twocolumn mode with @twocolumntrue. twocolumn=false denotes onecolumn mode with@twocolumnfalse. Instead of twocolumn=false, you can specify onecolumn (which defaults to true)
- one column works as two column=false. On the other hand, one column=false is equivalent to two column.

twoside sets both @twosidetrue and @mparswitchtrue. See Section 5.

textwidth sets textwidth directly. See Section 5.

textheight sets textheight directly. See Section 5.

reversemp | reversemarginpar makes the marginal notes appear in the *left* (inner) margin with @reversemargintrue. The option doesn't change *includemp* mode. It's set *false* by default.

Drivers

The package supports drivers *dvips*, *dvipdfm*, *pdftex*, *luatex*, *xetex* and *vtex*. You can also set *dvipdfm* for *dvipdfmx* and *xdvipdfmx* The options *dvipdfmx* and *xdvipdfmx* are also supported as aliases for the *dvipdfm* option. *pdftex* for *pdflatex*, and *vtex* for VTeX environment.

The driver options are exclusive. The driver can be set by either driver=\langle driver name \rangle or any of the drivers directly like pdftex. By default, geometry guesses the driver appropriate to the system in use. Therefore, you don't have to set a driver in most cases. However, if you want to use dvipdfm, you should specify it explicitly.

driver specifies the driver with driver= $\langle driver \ name \rangle$.

dvips, dvipdfm, pdftex, luatex, vtex, xetex, auto and none are available as a driver name. The names except for auto and none can be specified directly with the name without driver=.

driver=auto makes the auto-detection work whatever the previous setting is.

driver=none disables the auto-detection and sets no driver, which may be useful when you want to let other package work out the driver setting. For example, if you want to use crop package with *geometry*, you should call \usepackage[driver=none]{geometry} before the crop package.

dvips writes the paper size in dvi output with the special macro. If you use *dvips* as a DVI-to-PS driver, for example, to print a document with \geometry{a3paper,landscape} on A3 paper in landscape orientation, you don't need options -t a3 -t landscape to *dvips*.

dvipdfm works like *dvips* except for landscape correction. You can set this option when using *dvipdfmx* and *xdvipdfmx* to process the dvi output.

pdftex sets pdfpagewidth and pdfpageheight internally.

luatex sets pagewidth and pageheight internally.

xetex is the same as pdftex except for ignoring \pdf{h,v}origin undefined in XeLaTeX. This option is introduced in the version 5. Note that geometry.cfg in TeX Live, which disables the auto-detection routine and sets pdftex, is no longer necessary, but has no problem even though it's left undeleted. Instead of xetex, you can specify dvipdfm with XeLaTeX if you want to use specials of dvipdfm XeTeX supports.

vtex sets dimensions *mediawidth* and *mediaheight* for VTeX. When this driver is selected (explicitly or automatically), *geometry* will autodetect which output mode (DVI, PDF or PS) is selected in VTeX, and do proper settings for it.

If explicit driver setting is mismatched with the typesetting program in use, the default driver *dvips* would be selected.

Other options

The other useful options are described here.

verbose displays the parameter results on the terminal. verbose=false (default) still puts them into the log file.

reset sets back the layout dimensions and switches to the settings before *geometry* is loaded. Options given in <code>geometry.cfg</code> are also cleared. Note that this cannot reset *pass* and *mag* with *truedimen*. reset=false has no effect and cannot cancel the previous reset(= *true*) if any. For example, when you go

```
\documentclass[landscape]{article}
\usepackage[twoside,reset,left=2cm]{geometry}
```

with \ExecuteOptions{scale=0.9} in geometry.cfg, then as a result, landscape and left=2cm remain effective, and scale=0.9 and twoside are ineffective.

mag sets magnification value (*mag*) and automatically modifies *hoffset* and *voffset* according to the magnification:

mag=\(value\)

Note that $\langle value \rangle$ should be an integer value with 1000 as a normal size. For example, mag=1414 with a4paper provides an enlarged print fitting in a3paper, which is $1.414~(=\sqrt{2})$ times larger than a4paper. Font enlargement needs extra disk space. Note that setting mag should precede any other settings with "true" dimensions, such as 1.5truein, 2truecm and so on. See also truedimen option.

truedimen changes all internal explicit dimension values into *true* dimensions, e.g., 1in is changed to 1truein. Typically this option will be used together with *mag* option. Note that this is ineffective against externally specified dimensions. For example, when you set mag=1440, margin=10pt, truedimen, margins are not *true* but magnified. If you want to set exact margins, you should set like mag=1440, margin=10truept, truedimen instead.

pass disables all of the geometry options and calculations except *verbose* and *showframe*. It is order-independent and can be used for checking out the page layout of the documentclass, other packages and manual settings without *geometry*.

showframe shows visible frames for the text area and page, and the lines for the head and foot on the first page.

showcrop prints crop marks at each corner of user-specified layout area.

Processing options

Order of loading

If there's geometry.cfg somewhere TEX can find it, geometry loads it first. For example, in geometry.cfg you may write \ExecuteOptions{a4paper}, which specifies A4 paper as the default paper. Basically you can use all the options defined in geometry with \ExecuteOptions{}.

The order of loading in the preamble of your document is as follows:

- geometry.cfg if it exists.
- Options specified with \documentclass[\langle options \rangle] \{\ldots\}...\}.
- Options specified with \usepackage[\(\lambda ptions \rangle \)] \(\text{geometry} \)
- Options specified with \geometry{\(\lambda ptions \) \rangle, which can be called multiple times. (reset option will cancel the specified options ever given in \usepackage{geometry} or \geometry.)

Order of options

The specification of *geometry* options is order-independent, and overwrites the previous one for the same setting. For example,

```
[left=2cm, right=3cm]
```

is equivalent to

```
[right=3cm, left=2cm].
```

The options called multiple times overwrite the previous settings. For example,

```
[verbose=true, verbose=false]
```

results in

verbose=false

The [hmargin={3cm,2cm}, left=1cm] is the same as hmargin={1cm,2cm}, where the left (or inner) margin is overwritten by left=1cm.

The *reset* and *mag* are exceptions. The *reset* option removes all the geometry options (except *pass*) before it. If you set

```
\documentclass[landscape]{article}
\usepackage[margin=1cm,twoside]{geometry}
\geometry{a5paper, reset, left=2cm}
```

then *margin* = 1cm, *twoside* and *a5paper* are removed, and is eventually equivalent to

```
\documentclass[landscape]{article}
\usepackage[left=2cm]{geometry}
```

The *mag* option should be set in advance of any other settings with *true* length, such as left=1.5truecm, width=5truein and so on. The \mag primitive can be set before this package is called.

Priority

There are several ways to set dimensions of the *body*: scale, total, text and lines. The *geometry* package gives higher priority to the more concrete specification. Here is the priority rule for *body*.

$$\left\{\begin{array}{l} \textit{hscale} \\ \textit{vscale} \\ \textit{scale} \end{array}\right\} < \left\{\begin{array}{l} \textit{width} \\ \textit{height} \\ \textit{total} \end{array}\right\} < \left\{\begin{array}{l} \textit{textwidth} \\ \textit{textheight} \\ \textit{text} \end{array}\right\} < \textit{lines}$$

For example,

\usepackage[hscale=0.8, textwidth=7in, width=18cm]{geometry}

is the same as

\usepackage[textwidth=7in]{geometry}

Another example:

\usepackage[lines=30, scale=0.8, text=7in]{geometry}

results in

[lines=30, textwidth=7in]

Defaults

This section sums up the default settings for the auto-completion described later.

The default vertical margin ratio is 2/3, namely,

$$top: bottom = 2:3$$
 default (6)

As for the horizontal margin ratio, the default value depends on whether the document is onesided or twosided,

$$left (inner) : right (outer) = \begin{cases} 1 : 1 & default for one side \\ 2 : 3 & default for two side \end{cases}$$
 (7)

Obviously the default horizontal margin ratio for *oneside* is "centering".

The *geometry* package has the following default setting for *onesided* documents:

• scale=0.7 (body is $0.7 \times paper$)

- marginratio={1:1, 2:3} (1:1 for horizontal and 2:3 for vertical margins)
- ignoreall (the header, footer, marginal notes are excluded when calculating the size of *body*.)

For *twosided* document with twoside option, the default setting is the same as *onesided* except that the horizontal margin ratio is set to 2:3 as well.

Additional options overwrite the previous specified dimensions.

Auto-completion

Figure 7 shows schematically how many specification patterns exist and how to solve the ambiguity of the specifications. Each axis shows the numbers of lengths explicitly specified for body and margins. S(m,b) presents the specification with a set of numbers (margin, body) = (m, b).

For example, the specification width=14cm, left=3cm is categorized into S(1,1), which is an adequate specification. If you add right=4cm, it would be in S(2,1) and overspecified. If only width=14cm is given, it's in S(0,1), underspecified.

The *geometry* package has the auto-completion mechanism, in which if the layout parameters are underspecified or overspecified, *geometry* works out the ambiguity using the defaults and other relations. Here are the specifications and the completion rules.

• S(0,0) Nothing is specified. The *geometry* package sets *body* with the default scale (= 0.7).

For example, width is set to be $0.7 \times layoutwidth$. Note that by default layoutwidth and layoutheight will be equal to \paperwidth and \paperheight respectively.

Thus S(0,0) goes to S(0,1). See S(0,1).

• S(0,1) Only *body* is specified, such as width=7in, lines=20, body={20cm, 24cm}, scale=0.9 and so forth. Then *geometry* sets margins with the margin ratio. If the margin ratio is not specified, the default is used. The default vertical margin ratio is defined as




Figure 7. Specifications S(0,0) to S(2,1) and the completion rules (arrows). Column and row numbers denote the number of explicitly specified lengths for margin and body respectively. S(m,b) denote a specification with a set of the numbers (margin, body) = (m, b).

$$top: bottom = 2:3$$
 default (8)

As for the horizontal margin ratio, the default value depends on whether the document is onesided or twosided,

$$left(inner): right(outer) = \begin{cases} 1:1 & default for one side \\ 2:3 & default for two side \end{cases}$$
(9)

For example, if height=22cm is specified on A4 paper, *geometry* calculates top margin as follows:

$$top = (layoutheight - height) \times 2/5$$

= $(29.7 - 22) \times 2/5 = 3.08$ (cm) (10)

Thus top margin and body height have been determined, the specification for the vertical goes to S(1,1) and all the parameters can be solved.

• S(1,0) Only one margin is specified, such as bottom=2cm, left=1in, top=3cm, and so forth.

• If the margin ratio is *not specified, geometry* sets *body* with the default scale (=0.7). For example, if top=2.4cm is specified, *geometry* sets

height= 0.7\layoutheight (=0.7\paperheight by default)

then S(1,0) goes to S(1,1), in which *bottom* is calculated with *layoutheight* - (*height* + *top*) and results in 6.51cm on A4 paper if the layout size is equal to the paper size.

• If the margin ratio is specified, such as hmarginratio={1:2}, vratio={3:4} and so forth, geometry sets the other margin with the specified margin ratio. For example, if a set of options top=2.4cm, vratio={3:4} is specified, geometry sets bottom to be 3.2cm calculating

$$bottom = top/3 \times 4 = 3.2$$
cm

Thus S(1,0) goes to S(2,0).

Note that the version 4 or earlier used to set the other margin with the margin ratio. In the version 5, therefore, with the same specification, the result will be different from the one in the version 4. For example, if only top=2.4cm is specified, you got bottom=2.4cm in the version 4 or earlier, but you will get bottom=6.51cm in the version 5.

• S(2,1) The *body* and two *margins* are all specified, such as vdi-vide={1in,8in,1.5in}, left=3cm,width=13cm,right=4cm and so forth. Since *geometry* basically gives priority to *margins* if dimensions are overspecified, *geometry* forgets and resets *body*. For example, if you specify

\usepackage[a4paper,left=3cm,width=13cm,right=4cm] {geometry} width is reset to be 14cm because the width of a A4 paper is 21cm long.

Changing layout mid-document

The version 5 provides the new commands $\ensuremath{\texttt{Newgeometry}}$ and $\ensuremath{\texttt{Te-storegeometry}}$, which allow you to change page dimensions in the middle of the document. Unlike *geometry* in the preamble, $\ensuremath{\texttt{Newgeometry}}$ is available only after $\ensuremath{\texttt{begin}}$ document}, resets all the options ever specified except for the papersize-related options: $\ensuremath{\texttt{landscape}}$, $\ensuremath{\texttt{portrait}}$, and paper size options (such as papersize, paper=a4paper and so forth), which can't be changed with $\ensuremath{\texttt{Newgeometry}}$.

The command \restoregeometry restores the page layout specified in the preamble (before \begin{document}) with the options to \usepackage{geometry} and \geometry.

Note that both \newgeometry and \restoregeometry insert \clearpage where they are called.

Below is an example of changing layout mid-document. The layout L1 specified with hmargin=3cm (left and *right* margins are 3cm long) is changed to L2 with left=3cm, right=1cm and bottom=0.1cm. The layout L1 is restored with restoregeometry.

\usepackage[hmargin=3cm]{geometry\}

\begin{document}

Layout L1

\newgeometry{left=3cm,right=1cm,bottom=0.1cm}

Layout L2 (new)


\restoregeometry

Layout L1 (restored)

\newgeometry{margin=1cm,includefoot}

Layout L3 (new)

\end{document}



A set of commands \savegeometry{ $\langle name \rangle$ } and \loadgeometry{ $\langle name \rangle$ } is handy if you want to reuse more different layouts in your document. For example,

Examples

- 1. A onesided page layout with the text area centered in the paper. The examples below have the same result because the horizontal margin ratio is set 1:1 for oneside by default.
 - centering
 - marginratio=1:1
 - ullet vcentering
- 2. A twosided page layout with the inside offset for binding set to 1cm.
 - twoside, bindingoffset=1cm

In this case, textwidth is shorter than that of the default twosided document by $0.7 \times 1 \text{cm} \ (= 0.7 \text{cm})$ because the default width of *body* is set with scale=0.7, which means

```
width=0.7\layoutwidth
(=0.7\paperwidth by default)
```

- 3. A layout with the left, right, and top margin 3cm, 2cm and 2.5in respectively, with textheight of 40 lines, and with the head and foot of the page included in *total body*. The two examples below have the same result.
 - ullet left=3cm, right=2cm, lines=40, top=2.5in, includeheadfoot

- hmargin={3cm,2cm}, tmargin=2.5in, lines=40, includehead-foot
- 4. A layout with the height of *total body* 10in, the bottom margin 2cm, and the default width. The top margin will be calculated automatically. Each solution below results in the same page layout.
 - vdivide={*, 10in, 2cm}
 - bmargin=2cm, height=10in
 - bottom=2cm, textheight=10in

Note that dimensions for *head* and *foot* are excluded from *height* of *total* body. An additional *includefoot* makes *footskip* included in *totalheight*. Therefore, in the two cases below, *textheight* in the former layout is shorter than the latter (with 10in exactly) by *footskip*. In other words, height = textheight + footskip when includefoot = true in this case.

- bmargin=2cm, height=10in, includefoot
- bottom=2cm, textheight=10in, includefoot
- 5. A layout with textwidth and textheight 90% of the paper and with body centered. Each solution below results in the same page layout as long as layoutwidth and layoutheight are not modified from the default.
 - scale=0.9, centering
 - text={.9\paperwidth,.9\paperheight}, ratio=1:1
 - width=.9\paperwidth, vmargin=.05\paperheight, marginratio=1:1
 - hdivide={*,0.9\paperwidth,*}, vdivide={*,0.9\paperheight,*}
 (as for onesided documents)
 - margin={0.05\paperwidth,0.05\paperheight}

You can add heightrounded to avoid an "underfull vbox warning" like

Underfull \vbox (badness 10000) has occurred while \output is active.

See Section 5 for the detailed description about heightrounded.

- 6. A layout with the width of marginal notes set to 3cm and included in the width of *total body*. The following examples are the same.
 - marginparwidth=3cm, includemp
 - marginpar=3cm, ignoremp=false
- 7. A layout where *body* occupies the whole paper with A5 paper in land-scape. The following examples are the same.
 - a5paper, landscape, scale=1.0
 - landscape=TRUE, paper=a5paper, margin=Opt
- 8. A screen size layout appropriate for presentation with PC and video projector.

```
\documentclass{slide}
\usepackage[screen,margin=0.8in]{geometry}
...
\begin{slide}
...
\end{slide}
```

- 9. A layout with fonts and spaces both enlarged from A4 to A3. In the case below, the resulting paper size is A3:
 - a4paper, mag=1414

If you want to have a layout with two times bigger fonts, but without changing paper size, you can type:

• letterpaper, mag=2000, truedimen

You can add *dvips* option, that is useful to preview it with proper paper size by *dviout* or *xdvi*.

10. Changing the layout of the first page and leaving the others as default before loading *geometry*. Use *pass* option, \newgeometry and \restoregeometry.

```
\documentclass{book}
\usepackage[pass]{geometry}
  % 'pass' disregards the package layout,
  % so the original 'book' layout is memorized here.
\begin{document}
\newgeometry{margin=1cm}% changes the first page dimensions.
  Page 1
\restoregeometry % restores the original 'book' layout.
  Page 2 and more
\end{document}
```

11. A complex page layout.

```
\usepackage[
a5paper, landscape, twocolumn, twoside,
left=2cm, hmarginratio=2:1, includemp, marginparwidth=43pt,
bottom=1cm, foot=.7cm, includefoot, textheight=11cm,
heightrounded, columnsep=1cm, dvips, verbose]{geometry}
```