



Tune System Performance



Unit objectives

After completing this unit, you should be able to:

- Optimize system performance by by selecting a tuning profile that the tuned daemon manages.
- Prioritize or deprioritize specific processes, with the nice and renice commands.

Understand performance optimization

- Workload's requirement
- Adjusting settings based on requirement
- The tuned daemon
- Tuning profiles

Configuring Static Tuning

- When Service starts or
- Upon selection of new tuning profile
- Configures predefined kernel parameters
- Set for overall performance expectations
- Does not change over time

Configuring Dynamic Tuning

- The tuned daemon monitors system activity
- Adjust settings depending behavior change
- Continously monitor and adjust tuning fit workload's requirement
- Example of behavior changes:
 - Storage device experience high usage during startup, but minimal user activities.
 - Network device experience high usage during peak hours throughout the days.
- The tuned daemon capture these activities and adjust parameters to
 - allocate more CPU resource to storage during startup and
 - re-allocate CPU to Network device during the days

Tuning plug-ins

- disk: Sets different disk parameters, for example, the disk scheduler, the spin-down timeout, or the advanced power management.
- net: Configures the interface speed and the Wake-on-LAN (WoL) functionality.
- cpu: Sets different CPU parameters, for example, the CPU governor or the latency.
- Dynamic tuning is disabled.
- Enabled it by modifying /etc/tuned/tuned-main.conf
 - dynamic_tuning variable to 1

```
[root@host ~]$ cat /etc/tuned/tuned-main.conf
...output omitted...
# Dynamicaly tune devices, if disabled only static tuning will be used.
dynamic_tuning = 1
...output omitted...
# Update interval for dynamic tunings (in seconds).
# It must be multiply of the sleep_interval.
update_interval = 10
© Copyright Trainocate (M) 2020
```

Installing and enabling tuned

dnf install tuned

systemctl enable --now tuned

systemctl status tuned

Selecting a Tuning Profile 1/2

- with predefined settings
- Focus on
 - Low latency for storage and network
 - High throughput for storage and network
 - Virtual Machine performance
 - Virtualization host performance

Profiles distributed with RHEL v8/v9

Tuned Profile	Purpose
balanced	Ideal for systems that require a compromise between power saving and performance.
desktop	Derived from the balanced profile. Provides faster response of interactive applications.
throughput-performance	Tunes the system for maximum throughput.
latency-performance	Ideal for server systems that require low latency at the expense of power consumption.
network-latency	Derived from the latency-performance profile. It enables additional network tuning parameters to provide low network latency.
network-throughput	Derived from the throughput-performance profile. Additional network tuning parameters are applied for maximum network throughput.
powersave	Tunes the system for maximum power saving.
oracle	Optimized for Oracle database loads based on the throughput-performance profile.
virtual-guest	Tunes the system for maximum performance if it runs on a virtual machine.
virtual-host	Tunes the system for maximum performance if it acts as a host for virtual machines.


© Copyright Trainocate (M) 2020

Managing profiles from command line

- List all available profiles
- # tuned-adm list
- View current activated profile
- # tuned-adm active
- Switch profile
- # tuned-adm profile throughput-performance
- Ask for recommendation
- # tuned-adm recommend
- Disable tuning activity
- # tuned-adm off


Managing profiles from Web Console

For non-root, enable "Reuse my password for privileged tasks"




Managing profiles from Web Console

Click System > Enter Performance Profile




Managing profiles from Web Console v8.2




Managing profiles from Web Console

Select a profile > Click Change Profile



Managing profiles from Web Console

Verify changes



Influencing Process Scheduling

- Understand Linux Process Scheduling and Multitasking
- Relative Priorities
- Setting Nice Levels and Permissions

Understand Linux Process Scheduling and Multitasking

- Low end to High end Systems
- Single to Multiple CPUs
- CPU to execute instructions
 - dozens to millions
 - parallel
- Common traits: Requirement to run more process threads than CPU
- Linuxes uses time-slicing or multitasking
- Process Scheduler
 - switch processes in/out single core
 - Multiple processes running simultaneously
 - Has multiple scheduling policies for different processes

Relative Priorities

- Each process given level of importance
- Process Scheduler
 - Policy: SCHED_NORMAL, SCHED_FIFO, SCHED_RR, and SCHED_OTHER
 - default to SCHED_OTHER
- Use PR and NICE to determine importance
- NICE range -20 (highest) to 19 (lowest)
- NICE value 19, often don't get CPU time when system is busy
- Default NICE 0
- Child process inherit nice from parent
- No contention for CPU, higher NICE process may use all CPU

Nice Levels and Permissions

- Settings NICE
 - Only root can adjust process NICE level
 - Non-root users permitted to increase process NICE level of their own processes
- Reporting Nice Levels
 - PR : Scheduled priority : Set by Kernel
 - NI: NICE level: Set by user



Displaying NICE levels using TOP command

Result in real time

```
top - 08:10:36 up 5:28, 2 users, load average: 0.38, 0.29, 0.24
Tasks: 300 total, 7 running, 293 sleeping, 0 stopped, 0 zombie
%Cpu(s): 0.1 us, 1.8 sy, 0.0 ni, 95.6 id, 0.0 wa, 2.4 hi, 0.2 si, 0.0 st
MiB Mem : 1800.6 total, 157.4 free, 1295.2 used, 348.1 buff/cache
MiB Swap: 2048.0 total, 2029.0 free, 19.0 used. 319.5 avail Mem
```

PID	USER	PR	NI	VIRT	RES	SHR S	&CPU	%MEM	TIME+	COMMAND
7072	root	20	0	0	0	0 S	2.3	0.0	4:51.49	kvdo0:indexW
7073	root	20	0	0	0	0 S	1.3	0.0	4:31.10	kvdo0:indexW
5805	root	20	0	0	0	0 R	1.0	0.0	2:54.92	callbackW
5999	root	20	0	0	0	0 S	1.0	0.0	3:02.67	kvdol:indexW
6000	root	20	0	0	0	0 S	1.0	0.0	4:44.57	kvdol:indexW
5991	root	20	0	0	0	0 S	0.3	0.0	0:24.35	kvdo1:cpuQ1
1	root	20	0	246028	12080	7048 S	0.0	0.7	0:06.26	systemd
2	root	20	0	0	0	0 S	0.0	0.0	0:00.05	kthreadd
3	root	0	-20	0	0	0 I	0.0	0.0	0:00.00	rcu_gp
4	root	0	-20	0	0	0 I	0.0	0.0	0:00.00	rcu_par_gp
6	root	0	-20	0	0	0 I	0.0	0.0		kworker/0:0H
8	root	0	-20	0	0	0 I	0.0	0.0	0:00.00	mm_percpu_wq
9	root	20	0	0	0	0 S	0.0	0.0	0:01.10	ksoftirqd/0
10	root	20	0	0	0	0 R	0.0	0.0	0:00.87	rcu_sched
11	root	rt	0	0	0	0 S	0.0	0.0	0:00.00	migration/0
12	root	rt	0	0	0	0 S	0.0	0.0	0:00.00	watchdog/0
13	root	20	0	0	0	0 S	0.0	0.0	0:00.00	cpuhp/0
14	root	20	0	0	0	0 S	0.0	0.0	0:00.00	cpuhp/1
15	root	rt	0	0	0	0 S	0.0	0.0	0:00.00	watchdog/1
16	root	rt	0	0	0	0 S	0.0	0.0	0:00.00	migration/1
17	root	20	0	0	0	0 S	0.0	0.0	0:00.37	ksoftirqd/1
1 0	~~~+	^	-20	0	0	ОТ	0 0	0 0	0.00 00	lerrantean/1.0#-leb1aaled

Displaying NICE levels using PS command

- Show unsorted process with extra information
- # ps axo pid,comm,nice,cls
- Show process with extra information and sort by NICE ascendingly
- # ps axo pid,comm,nice,cls --sort=nice
- Show process with extra information and sort by NICE descendingly
- # ps axo pid,comm,nice,cls --sort=-nice

```
PID COMMAND
                      NI CLS
  1 systemd
                           TS
  2 kthreadd
                           TS
  3 rcu gp
                     -20
                           TS
  4 rcu par gp
                     -20
                           TS
  6 kworker/0:0H
                     -20
                           TS
                     -20
   mm percpu wq
                           TS
  9 ksoftirqd/0
                           TS
 10 rcu sched
                           TS
 11 migration/0
                           FF
 12 watchdog/0
                           FF
13 cpuhp/0
                           TS
 14 cpuhp/1
                           TS
 15 watchdog/1
                           FF
 16 migration/1
                           FF
 17 ksoftirgd/1
                           TS
 19 kworker/1:0H-kb-20
                           TS
 20 cpuhp/2
                           TS
 21 watchdog/2
                           FF
 22 migration/2
                           FF
23 ksoftirqd/2
                           TS
   kworker/2:0H-kb -20
                           TS
 26 cpuhp/3
                           TS
 27 watchdog/3
                           FF
 28 migration/3
                           FF
 29 ksoftirqd/3
                           TS
```

Displaying NICE levels using HTOP command

```
1 [|||
                                                 4.8%1
                                                         Tasks: 59, 65 thr; 4 running
   4.8%]
                                                         Load average: 0.11 0.28 0.28
                                                         Uptime: 05:56:04
                                                 5.4%1
   4.0%1
4 [ ] |
Mem[|||||||||1.27G/1.76G]
                                         28.8M/2.00G]
Swp[
  PID USER
                PRI
                     NI
                         VIRT
                                RES
                                      SHR S CPU%
                                                 MEM%
                                                         TIME+ Command
14384 root
                 20
                        1153M 17516
                                    13004 S
                                                   0.9
                                                        0:00.00 /usr/libexec/udisks2/udisksd
14280 root
                 2.0
                      0 1153M 17516 13004 S
                                             0.0
                                                  0.9
                                                        0:00.00 /usr/libexec/udisks2/udisksd
                                                        0:00.00 /usr/libexec/udisks2/udisksd
14267 root
                      0 1153M 17516
                                    13004 S
14265 root
                 20
                      0 1153M 17516 13004 S
                                             0.0
                                                  0.9
                                                       0:00.00 /usr/libexec/udisks2/udisksd
 6845 root
                 20
                        459M
                              1640
                                      840 S
                                             0.0
                                                  0.1 0:04.53 /usr/bin/vmhqfs-fuse .host:/ /mnt/hqfs -o subtype=x
                         459M
                                      840 S
                                                       0:00.82 /usr/bin/vmhqfs-fuse .host:/ /mnt/hqfs -o subtype=x
 6897 root
                 20
                               1640
                                             0.0
 6896 root
                 20
                         459M
                               1640
                                      840 S
                                             0.0
                                                  0.1 0:00.87 /usr/bin/vmhqfs-fuse .host:/ /mnt/hqfs -o subtype=x
 6895 root.
                 20
                         459M
                               1640
                                      840 S
                                             0.0
                                                  0.1 0:00.89 /usr/bin/vmhqfs-fuse .host:/ /mnt/hqfs -o subtype=x
                                                  0.1 0:00.00 /usr/bin/vmhgfs-fuse .host:/ /mnt/hgfs -o subtype=x
 6852 root
                 20
                         459M 1640
                                      840 S
                                             0.0
                              1640
                                      840 S
                                                  0.1 0:00.98 /usr/bin/vmhqfs-fuse .host:/ /mnt/hqfs -o subtype=x
 6850 root
                 20
                        459M
                                             0.0
                                      840 S
                                                       0:00.92 /usr/bin/vmhqfs-fuse .host:/ /mnt/hqfs -o subtype=x
                 20
                         459M
                              1640
                                             0.0
 6849 root
                         195M 28116 12188 S
                                             0.0
                                                       0:01.92 /usr/sbin/dmeventd -f
 5840 root
 5998 root
                 20
                         195M 28116 12188 S
                                             0.0
                                                  1.5
                                                       0:00.16 /usr/sbin/dmeventd -f
 5842 root
                      0 195M 28116 12188 S
                                             0.0
                                                  1.5
                                                       0:01.03 /usr/sbin/dmeventd -f
 2334 root
                 20
                        186M 10988
                                     9420 S
                                             0.0
                                                  0.6 0:00.07 login -- root
12365 root
                 20
                      0 26692
                               4820
                                     2820 S
                                             0.0
                                                  0.3 0:00.04 -bash
                                                       0:00.02 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsm
 1970 dnsmasq
                      0 71888
                               1448
                                     1012 S
                                             0.0
 1971 root
                 20
                      0 71860
                                428
                                        0 S
                                             0.0
                                                  0.0 0:00.00 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsm
                      0 195M 3316
 1662 rtkit
                                     2980 S
                                             0.0
                                                  0.2 0:00.10 /usr/libexec/rtkit-daemon
 1491 user
                 20
                      0 93988
                               5924
                                     4292 S
                                              0.0
                                                  0.3 0:00.28 /usr/lib/systemd/systemd --user
 1872 user
                 20
                      0 82592
                               4116
                                     3628 S
                                             0.0
                                                  0.2 0:00.01 /usr/bin/dbus-daemon --session --address=systemd: -
                      0 82592
                               4116
                                     3628 S
                                                  0.2 0:00.00 /usr/bin/dbus-daemon --session --address=systemd: -
 1883 user
 1612 user
                 20
                         293M
                               6144
                                     4960 S
                                             0.0
                                                  0.3 0:00.08 /usr/bin/pulseaudio --daemonize=no
                         293M
                                     4960 S
                                             0.0
 1871 user
                 20
                               6144
                                                  0.3 0:00.00 /usr/bin/pulseaudio --daemonize=no
 1537 user
                        167M
                               3904
                                        0 S
                                             0.0
                                                  0.2 0:00.00 (sd-pam)
                      0 93968
                                     4328 S
 1490 root
                 20
                               5944
                                             0.0
                                                  0.3 0:00.26 /usr/lib/systemd/systemd --user
                                             0.0
 1665 root
                      0 82592
                               4328
                                     3844 S
                                                  0.2 0:00.02 /usr/bin/dbus-daemon --session --address=systemd: -
 1699 root
                 2.0
                      0 82592
                               4328
                                     3844 S
                                             0.0
                                                  0.2 0:00.00 /usr/bin/dbus-daemon --session --address=systemd: -
 1540 root
                      0 155M
                               4068
                                        0 S
                                             0.0
                                                  0.2 0:00.00 (sd-pam)
                                     1792 S
                                                       0:00.01 /usr/sbin/atd -f
 1480 root
                      0 42624
                               1996
                                             0.0
 1478 root
                 2.0
                      0 27876
                              3060
                                     2200 S
                                             0.0
                                                  0.2 0:00.20 /usr/sbin/crond -n
                        204M
 1474 root
                 20
                              6488
                                     4388 S
                                             0.0
                                                  0.4 0:00.94 /usr/sbin/rsyslogd -n
                                                       0:00.02 /usr/sbin/rsyslogd -n
 1487 root
                 20
                               6488
                                     4388 S
                                             0.0
                                                  0.4
                         204M 6488 4388 S 0.0 0.4 0:00.88 /usr/sbin/rsyslogd -n
 1483 root
     F2Setup F3SearchF4FilterF5Tree F6SortByF7Nice -F8Nice +F9Kill F10Quit
```

Set NICE Levels – starting new process

- Default, child process start inherit from parent
- Process start from command line, inherit from shell
- Typically new processes runs with NICE value 0
- Example: Start a process with default NICE

```
[user@host ~]$ sha1sum /dev/zero &
[1] 3480
[user@host ~]$ ps -o pid,comm,nice 3480
PID COMMAND NI
3480 sha1sum 0
```

Example: Start a process with NICE value = 10

```
[user@host ~]$ nice sha1sum /dev/zero &
[1] 3517
[user@host ~]$ ps -o pid,comm,nice 3517
PID COMMAND NI
3517 sha1sum 10
```

Set NICE Levels – starting new process

Example: Start a process with custom NICE

```
[user@host ~]$ nice -n 15 sha1sum &
[1] 3521
[user@host ~]$ ps -o pid,comm,nice 3521
PID COMMAND NI
3521 sha1sum 15
```

Important:

Unpriviledged users may only increase NICE value from current to maximum of 19.

Root may reduce it to -20

Set NICE Levels – on existing process

Example: Change process ID 3521 NICE value to 19

```
[user@host ~]$ renice -n 19 3521
3521 (process ID) old priority 15, new priority 19
```

- Example: Using htop (F7 & F8)
- Important:

Unpriviledged users may only increase NICE value from current to maximum of 19.

Root may reduce it to -20

- 1. Change existing process id 1234 NICE to -15.
 - a) chprio -pri -5 1234
 - b) chprio 1234 –prio -5
 - c) kill -15 1234
 - d) renice –n -15 1234
- 2. Which are possible commands to see NICE value? [Choose all applies]
 - a) ps aux
 - b) ps axo pid,comm,ni
 - c) top
 - d) ps -ef
- 3. User james attempted his change own process NICE value # renice -5 25999 but got error saying permission denied. What is the possible reason?
 - a) Underpriviledge user are not permitted to user renice command
 - b) Underpriviledge user can only increase NICE value but never decrease it
 - c) User james did not have appropriate ACL permission to the file
 - d) User james did not have appropriate permission to the process

- 1. Change existing process id 1234 NICE to -15.
 - a) chprio -pri -5 1234
 - b) chprio 1234 –prio -5
 - c) kill -15 1234
 - d) renice -n -15 1234
- 2. Which are possible commands to see NICE value? [Choose all applies]
 - a) ps aux
 - b) pa axo pid,comm,ni
 - c) top
 - d) ps -ef
- 3. User james attempted his change own process NICE value # renice -5 25999 but got error saying permission denied. What is the possible reason?
 - a) Underpriviledge user are not permitted to user renice command
 - b) Underpriviledge user can only increase NICE value but never decrease it
 - c) User james did not have appropriate ACL permission to the file
 - d) User james did not have appropriate permission to the process

- 4. Devops team install and configure a database system. It was running fine until next reboot, the database system misbehave. You suspest this is due to dynamic tuning by the kernel. How do you stop the dynamic tuning?
 - a) tuned --stop
 - b) tuned --disable
 - c) systemctl stop tuned
 - d) tuned-adm off
- 5. True or False: Higher NICE value has more priority

- 4. Devops team install and configure a database system. It was running fine until next reboot, the database system misbehave. You suspest this is due to dynamic tuning by the kernel. How do you stop the dynamic tuning?
 - a) tuned --stop
 - b) tuned --disable
 - c) systemctl tuned stop
 - d) tuned-adm off
- 5. True or False: Higher NICE value has more priority

Unit summary

Having completed this unit, you should be able to:

- Understand performance optimization
- Manage and Select Tuning Profiles
- Influence Process Scheduling