

The leporello class

A LaTeX document class to create folded leaflets using columns and boxes

Jasper Habicht *

Version 1.0.3, released on 15 September 2025

1 Introduction

The leporello class is a LaTeX document class to create folded leaflets with the following key features:

- The document layout consists of a specific number of pages that can have varying widths and are placed next to each other. Each page contains one frame to contain typeset material.
- Material is typeset in boxes and boxes are positioned in columns which in turn are placed into the frames on the pages of the document.
- Columns are predefined and then placed into the frame of a page in the document layout. This way, columns can be used on pages with varying widths.
- Boxes can have padding (including bleed) and a background and are positioned inside a column.

A folded leaflet is sometimes called leporello in reference to the servant of Don Giovanni (known from the opera by Mozart) who, at one point, unfolds a lengthy zig-zag folded list of his master's love affairs.

There are some requirements for the creation of print data for high-quality folded leaflets: Especially if the leaflet is folded inward, the inner pages should be a bit less wide, so in general the pages of a leaflet are not of the exact same width (although the widths only differ slightly). Also, borderless printing requires that the print data adds a so-called bleed area added to the layout if the final document into which the typeset material extends. This area is trimmed off eventually to avoid unprinted edges due to natural movement of the paper during guillotining. Crop marks need to be

^{*} E-mail: mail@jasperhabicht.de. Title image: © 2025 Hannah Klöber.

added to the print data showing the layout of the final document. This packages takes into account all these requirements while providing a lot of customization.

This document class is still in an early development phase which means that bugs cannot be ruled out and some things may not work properly. Also, updates may be published frequently. The author is grateful for reporting any bugs via GitHub at https://github.com/jasperhabicht/leporello/issues. A site for asking questions about the document class and for suggestions for improvement is available at https://github.com/jasperhabicht/leporello/discussions.

2 Loading the document class

Use \documentclass{leporello} to load the document class. The document class loads the graphicx and the l3draw package.

The document class is based on the article class to enable basic typesetting commands. But due to the redefinition of the layout, certain functions of the article class, such as placing material into the header, the footer or the margin (which do not exist in the leporello layout) or using floats or footnotes won't work. Instead of floats, the document class provides a sophisticated alignment mechanism for boxes. Instead of footnotes, it provides its own note mechanism.

```
\leporelloset[<prefix>]{<options>}
```

Use \leporelloset or use the optional argument of the \documentclass command to globally set the document layout. The optional argument can be used to set a common prefix to all options. Options should be used without the global/ prefix when used as option to the \documentclass command. The following options are available:

```
global/columns={<list of dimensions>}
global/two columns
global/three columns
global/four columns
global/four columns wrap
global/five columns
global/six columns
```

Expects a comma-separated list of dimensions that describe the widths of the columns in the layout. If columns is not specified, the class assumes the default value of 97mm, 100mm, 100mm. The width of the document layout is automatically calculated from the dimensions set via columns.

A few column layouts are predefined. These do not expect a value. The layouts will set the following list of dimensions:

| Key | List of dimensions |
|-------------------|--|
| two columns | 99 mm, 99 mm |
| three columns | 97 mm, 100 mm, 100 mm |
| four columns | 99 mm, 99 mm, 99 mm, 100 mm |
| four columns wrap | 97 mm, 99 mm, 100 mm, 101 mm |
| five columns | 97 mm, 97 mm, 97 mm, 99 mm, 100 mm |
| six columns | 99 mm, 99 mm, 96 mm, 96 mm, 100 mm, 100 mm |

```
global/layout height={<dimension>}
```

Expects a dimension that sets the height of the final layout. If global/layout height is not specified, the class assumes the default value of 210mm (the height of A4 landscape).

global/auto typeset

If set, the columns are automatically typeset according to the order of the definition of the columns. This means that in a three-column layout for example, the first three defined columns will be placed on the first PDF page followed by the next three defined columns on the next PDF page. This key does not expect a value.

global/show frames

If set, frames around the single pages (columns) are shown. This key does not expect a value.

global/show ids

If set, the IDs of the boxes are shown. This key does not expect a value. The IDs of the boxes are integers starting from I and increasing in the order of typesetting of the boxes.

global/prepress

If set, the paper size is increased at all four edges by the width of the info area and crop marks are placed at the corners. This key does not expect a value.

```
global/info area={<dimension>}
```

Expects a dimension for the width of the info area that is shown if global/prepress is set. If global/info area is not specified, the class assumes the default value of 10mm.

```
global/bleed={<dimension>}
```

Expects a dimension for the width of the bleed that is added to boxes with background and other material reaching to the edges of the document layout. If global/bleed is not specified, the class assumes the default value of 3mm.

\leporellobleed

Retrieves the width of the bleed in pt.

\leporellolayoutheight

Retrieves the height of the layout in pt.

\leporelloboxwidth

Retrieves the width of the current box including padding, but without bleed, in pt. The width of the box excluding padding can be retrieved with the \linewidth command.

3 Defining columns

Columns are grouped material to be typeset onto a specific page of the folded leaflet. A column can contain anything that can be placed in a TeX box in general, but the typical use of a column is to only serve as a frame to which boxes are attached. While the package provides a flow mechanism across

boxes, no such mechanism is provided for columns. Thus, if a column contains more than fits into it, the relevant parts just spill over the frame edges.

```
\begin{leporellocolumn}{<string>}
  <body>
\end{leporellocolumn}
```

A column is defined by the leporellocolumn environment which takes one mandatory argument taking the name of the column. A single dot (.) is reserved as name for an empty column.

4 Positioning boxes

```
\begin{leporellobox}[<options>]
  <body>
\end{leporellobox}
```

Boxes can be positioned inside of columns. They can contain anything that can be placed in a TeX box in general. A box is defined by the leporellobox environment which takes one optional argument to set box-specific options. Options should be used without the box/ prefix when used as option to the leporellobox environment. These are the following:

```
box/name={<string>}
```

Expects a (unique) string denoting the name of the box which can be used for attaching boxes to one another or for assigning boxes for the flow mechanism. This key can only be set locally to the leporellobox environment.

```
box/parent={<string>}
```

Expects a string denoting the name of the box to which the current box is aligned. If not specified, the current column box is assumed as parent box. The parent box needs to be in the same column as the box that should be aligned to it. This key can only be set locally to the leporellobox environment.

```
box/align parent={<tuple of poles>}
```

Expects a comma-separated list of two items (a tuple) which denotes the horizontal and vertical pole of which the intersection defines the coordinate of the parent box (per default this is the current column box) that serves as anchor to align the current box. If not specified, the default value 1, t is assumed, denoting the top left corner. Available poles are:

| Key | Meaning |
|-----|------------------------------|
| 1 | left edge of the box |
| hc | horizontal center of the box |
| r | right edge of the box |
| t | top edge of the box |
| VC | vertical center of the box |
| b | bottom edge of the box |

```
box/align self={<tuple of poles>}
```

Expects a comma-separated list of two items (a tuple) which denotes the horizontal and vertical pole of which the intersection defines the coordinate of the current box that serves as anchor to align the current box to parent box (per default this is the current column box). If not specified, the default value 1, t is assumed, denoting the top left corner. Available poles are the same as for box/align parent.

```
box/offset={<tuple of dimensions>}
```

Expects a comma-separated list of two dimensions (a tuple) which defines the offset of the anchor set via box/align parent and box/align self. The first dimension is the offset to the right, the second dimension the offset downwards. If not specified, the default value omm, omm is assumed. Internally, the value is parsed as a floating point variable.

```
box/width={<dimension>}
```

Expects a dimension to explicitly set the width of the current box. If not specified, the box is as wide as the parent column.

```
box/height={<dimension>}
```

Expects a dimension to explicitly set the height of the current box. If not specified, the box takes its natural height which means that it is as high as necessary to fit the contents.

```
box/stretch
```

If set, the box is stretched until its relevant edge (the bottom edge if aligned at the top, the top edge if aligned at the bottom, or the left or right edge in vertical typesetting) meets the edge of the parent column. This key does not expect a value.

This key can also help to align the relevant edges in cases where stretchable glue close to the edge would otherwise make the box overlap the edge of the parent column.

!

The box/stretch key only affects the outer box. Therefore, if a box is stretched and has an offset, the height (or width in vertical typesetting) needs to be given explicitly as the text will flow out of the box otherwise.

```
box/padding left={<dimension>}
box/padding right={<dimension>}
box/padding top={<dimension>}
box/padding bottom={<dimension>}
box/padding={<key-value list>}
box/no padding
```

Each of the four keys box/padding left, box/padding right, box/padding top and box/padding bottom expects a dimension to describe the padding of the contents from the relevant edge of the box. If not specified, the default value of 7.5mm is assumed.

All four padding settings can also be stated using the box/padding key and the subkeys left, right, top, bottom. Using this syntax, the default value of the padding setting would be expressed as box/padding={left=7.5mm, right=7.5mm, top=7.5mm, bottom=7.5mm}.

The key box/no padding sets all paddings to zero. This key does not expect a value.

```
box/pre={<code>}
```

Expects a token list that is placed before the actual contents of the box. Should not contain typeset material. This can be handy, if multiple boxes should be styled in a similar way.

```
box/background color={<color name>}
box/background color={none}
```

Expects a color name as defined via l3color or none which will not fill the background. If not specified, the default value of none is assumed.

```
box/background code={<code>}
```

Expects typeset material that will be placed into the background of the box aligned at the upper left corner of the box. THe typeset material is clipped to the size of the box.

```
box/bleed={<list of values>}
```

Expects a comma-separated list consisting of up to four items with the values $\, l \,$ and $\, r \,$, $\, t \,$ and $\, b \,$ that describe the edges (left, right, top and bottom) where bleed should be added to the box. Note that bleed is never added to the inner edges where the columns meet.

```
box/store width={<control sequence>}
```

Expects a single control sequence (macro) to store the width of the current box.

```
box/store height={<control sequence>}
```

Expects a single control sequence (macro) to store the height of the current box.

```
box/flow into={<string>}
```

Expects a string denoting the name of the box into which typeset material will flow into if it does not fit into the current box. The box to flow into can be in a following column or on a following page. See section 6 below. This key can only be set locally to the leporellobox environment.

5 Typesetting boxes into columns

```
\leporellotypesetcolumns[<options>]{<list of strings>}
```

The command \leporellotypesetcolumns can be used to typeset previously defined columns into the document. The command expects as its single mandatory argument a comma-separated list of names of previously defined columns. These are then placed onto a document page from left to right while the width is taken from the setting via the global/columns key and the height is taken from the setting via the layout height key. With a ., an empty column can be added to the list.

The command takes one optional argument. Options should be used without the typeset/prefix when used as option to the \leporellotypesetcolumns command. The command accepts the following options:

```
typeset/reverse layout
```

If set, the widths of the columns are reversed, but the placement of the columns is still from left to right. This option does not take a value. The option should be used to typeset the verso of a folded leaflet that naturally has the widths of the columns reversed. This key does not expect a value.

typeset/reverse order

If set, the order of the columns is reversed, which means that the columns are typeset from right to left. Pagination is not affected. This key does not expect a value.

typeset/reverse pagination

If set, the pagination of the columns is reversed. This key does not expect a value.

typeset/alternate layout

If set, the widths of the columns are reversed in every second page. This key is set to true per default. Use typeset/alternate layout=false to disable this function.

typeset/continuous pagination

If set, columns are numbered continuously from left to right. Otherwise, the pagination starts on the last column of every odd shipout page, continues from left to right over the columns on the following shipout page and eventually from left ro right over the remaining columns on the first page. For example, in a document with three columns per shipout page the pagination would be 5, 6, 1 and 2, 3, 4 and then on the next two shipout pages 11, 12, 7 and 8, 9, 10. This key does not expect a value.

6 Flow mechanism

Typeset material can flow from one box to another box. To this end, the key box/flow into can be set to the relevant box and assigned the name of the box to flow into as value. The name of the relevant box can be set via the box/name key. If two or more boxes are connected this way, contents of the boxes are always concatenated.

Prior to shipping out a (PDF) page, all material in boxes that have the box/flow into key set (and where another box with the relevant name exists) is collected and shipped out to pages of the size of the boxes the relevant material should flow into. The resulting boxes are saved internally and the shipout of these boxes is discarded. The saved boxes are then placed into the relevant boxes on the (PDF) page which is eventually shipped out.

\leporelloboxbreak

The flow mechanism works across multiple boxes. But due to the way the typesetting mechanism of TeX works, it needs some manual adjustment if the typeset material flows across boxes of different width. In this case, the command \leporelloboxbreak or \pagebreak should be inserted at the point where the break should take place. The command \leporelloboxbreak is especially suited for justified typesetting as it will keep the last line before the break justified in contrast to the \pagebreak command.

Typeset material can only flow into boxes that are defined later in the code. If typeset material should flow backwards on the same page, this can be achieved using the key reverse order on the relevant page.

6.1 Right-to-left and vertical typesetting

The document class natively supports right-to-left and vertical typesetting using the mechanisms provided by LuaLaTeX. The babel package also makes use of the mechanisms for bidirectional typesetting provided by LuaLaTeX, which means that this package will work best with a combination of LuaLaTeX and babel for right-to-left or vertical typesetting.

If right-to-left typesetting is activated, the layout, order and pagination of the layout will be reversed automatically.

If the bidi package is used (which is used by the polyglossia package), the following addition to the preamble is needed to enable right-to-left typesetting:

```
{leporello/typeset/before}{\setLTR}
\AddToHook{leporello/box/begin}{\setRTL}
```

In general, it has to be made sure that only the inner boxes are affected by the right-to-left or vertical typesetting mechanism and not the overall layout.

Vertical typesetting will typically affect the measurements of the boxes. The package sets to true the boolean \l_leporello_layout_vertical_ltr_bool for vertical typesetting from left to right (for example used to write traditional Mongolian). The package sets to true the boolean \l_leporello_layout_vertical_rtl_bool for vertical typesetting from right to left (for example used to write Chinese, Japanese or Korean).

7 Other settings

7.1 Inserting images

One way to insert images is via the \includegraphics command provided by the graphicx package. Using the box/background code key, images can be added to the background of a box.

```
\leporelloimage[<options>]{<file name>}
```

With the command \leporelloimage images that cover full boxes can be inserted. This command can be placed in a leporellobox with zero padding and it should only be used inside a leporellobox environment. The command has one mandatory argument that takes a relative path and file name to select the image to be inserted. It also has one optional argument to take options to be used without the image/ prefix. The following options are available:

```
image/clip width={<dimension>}
image/clip height={<dimension>}
```

Expect a dimension depicting the width and the height of the boxed image.

```
image/scale={<floating point number>}
```

Expects a floating point number depicting the scaling factor of the image. This factor will not affect the size of the box.

```
image/width={<dimension>}
image/height={<dimension>}
```

Expect a dimension to explicitly set the width and the height of the image. Setting image/width will override a image/scale value. Setting image/height will override a image/width or image/scale value. The aspect ratio of the original image will always be kept.

```
image/offset={<tuple of dimensions>}
```

Expects a comma-separated list consisting of two values (tuple) that describe the offset of the image that will be positioned per default so that the upper left corner sits at the upper left corner of the box. A positive offset will shift the image in upper left direction. Internally, the value is parsed as a floating point variable.

```
image/ignore padding={<list of values>}
```

Expects a comma-separated list consisting of up to four items with the values 1 and r, t and b that describe the edges (left, right, top and bottom) where the image should ignore the padding of the current box.

```
image/fill bleed
```

If set, the image will spread into the bleed. This will result in a shift of the image by the size of the bleed which may need to be accounted for using image/offset. This key does not expect a value.

7.2 Defining colors

The package uses the color model of the l3color module. The xcolor package is not supported. To provide a user interface to define and select colors, the commands \leporellocolordefine and \leporellocolorselect are defined.

```
\leporellocolordefine{<string>}{<color model>}{<list of values>}
```

The command \leporellocolordefine takes three arguments, the first being the name of the color to be defined. The second argument takes the color model (for example rgb or cmyk) and the third argument takes the color values. For more information about which color models are supported, please refer to the documentation of the l3color module.

```
\leporellocolorselect{<string>}
```

The command \leporellocolorselect takes the name of the previously defined color as argument. All following objects are affected by this color setting. To colorize only a few letters, use curly braces for grouping.

7.3 Defining styles

```
\leporellosetstyle[\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\rangerefix\
```

In order to simplify the setting of recurring options to the leporellobox environment, it is possible to group several of these options as style via the \leporellosetstyle command which takes as first argument the name of the newly defined style and as second argument the releevant options (key-value pairs). The style can then be used like an option to any leporellobox environment. The optional argument can be used to set a common prefix for the style definition. The following two expressions are equivalent:

```
[box]{align bottom}{
  align parent={l,b},
  align self={l,b}
}

\leporellosetstyle{box/align bottom}{
  box/align parent={l,b},
  box/align self={l,b}
}
```

7.4 Notes

Due to the layout specifications, this document class does not support footnotes. Instead, it provides its own note mechanism that allows to insert marks for notes and printing the notes combined as list.

```
\leporellonote[<integer>]{<code>}
```

The command \leporellonote increases the internal note counter and inserts a mark. It stores the actual note provided in the argument in an internal sequence. Using the optional argument, the counter for the mark can be set explicitly.

\leporelloprintnotes

The command \leporelloprintnotes prints all notes as list. Per default, this is an enumerate environment. It also empties the internal sequence to store notes.

Using the command \leporelloset, note marks and note lists can be styled. The following options are available:

```
notes/mark cmd={<control sequence>}
```

Expects a control sequence that takes exactly one argument being the value of the counter of the note. The counter has the L3 integer type. To print the marks as Roman numerals in square brackets separated by a space, for example, the following settings could be used:

```
{\squaredroman}{m}{\,[\romannumeral #1]}
\leporellonotesset{
  mark cmd = {\squaredroman}
}
```

```
notes/list style={<string>}
```

Expects a name of the list environment such as enumerate or itemize. Using the enumitem package, for example, a custom list can be created and styled individually.

7.5 Hooks

The package offers three pairs of hooks that are positioned at the start and end of columns and boxes allowing for inserting code.

The package uses the hook begindocument/before to insert layout-related settings as well as the hook shipout/foreground to insert code to draw crop marks. It uses the hook enddocument to insert code for the automatic typesetting mechanism that is activated via the key global/auto typeset. It also uses the hook label to change the default code for the \label so that it immediately writes to the auxiliary file.

The flow mechanism makes use of the hook shipout/before to insert code to break typeset material into boxes and build/page/after to update the current page number. The inserted code is removed after the flow mechanism has finished.


The hooks leporello/break-flow/before, leporello/typeset/before and leporello/box/begin are used to set and unset right-to-left and vertical typesetting mode.

Finally, hooks are used to issue warnings if the commands \footnote, \footnotemark and \footnotetext or the environments figure or table are used as this document class does not support these commands and environments.

| Hook | Position |
|-----------------------------|---|
| leporello/column/begin | before the code block stored via the leporellocolumn environment is typeset to the column box, preceded by a line of code that saves the name of the current column into \l_leporello_current_column_str |
| leporello/column/end | after the code block stored via the leporellocolumn environment is typeset to the column box |
| leporello/box/begin | before the code block stored via the leporellobox environment is typeset into the relevant box which is preceded by a line of code that saves the ID of the current column into \l_leporello_current_box_int and immediately followed by the code defined via the box/pre key |
| leporello/box/end | after the code block stored via the leporellobox environment is typeset to the relevant box |
| leporello/typeset/before | immediately after the start of the group that contains the typeset column |
| leporello/typeset/after | immediately before the end of the group that contains the typeset column |
| leporello/break-flow/before | before the flow mechanism is initiated that breaks material into boxes |
| leporello/break-flow/after | after the flow mechanism has finished |

8 Examples

The following examples show some of the basic ideas of the package by providing a code example and showing its output.




```
\documentclass[
  prepress,
  show frames,
  show ids
]{leporello}
\leporellosetstyle[box]{align bottom}{
  align parent={l,b},
  align self={l,b}
}
\begin{leporellocolumn}{example-a}
\begin{leporellobox}[
  background color={black!10},
  height={50mm},
  bleed={l,t}
]
foo
\end{leporellobox}
\end{leporellocolumn}
\begin{leporellocolumn}{example-b}
\begin{leporellobox}[
  background color={black!10},
  offset={omm,5omm},
  stretch,
  bleed={b}
]
\end{leporellobox}
\end{leporellocolumn}
```

```
\begin{leporellocolumn}{example-c}
\begin{leporellobox}[
   background color={black!10},
   align bottom,
   bleed={r,b}
]
baz
\end{leporellobox}
\end{leporellocolumn}
\begin{document}
\leporellotypesetcolumns{
   example-a, example-b, example-c
}
\end{document}
```

This example shows the use of the global/prepress key that adds crop marks to the layout. It also shows how the global/show frames key adds frames around the columns. Finally, the global/show id key adds the box IDs to the boxes.

The default layout has three pages which are shown here. Three columns named example-a, example-b and example-c are defined and contain one box each. A custom style is defined to combine the two keys needed to bottom-align the third box. A fixed height is set to for the first box and the second box has an offset and its height stretched to the bottom of the column. Bleed is added to the relevant edges of the three columns.



```
\documentclass[
  prepress,
  show frames,
  show ids
]{leporello}
```

```
\usepackage{lipsum}
\begin{leporellocolumn}{example-a}
\begin{leporellobox}[
  background color={black!10},
  height={75mm},
  bleed={t},
  flow into={box-b}
\lipsum[1-3]
This is another paragraph without any particular meaning. The sole
reason for its existence is to show how this \leporelloboxbreak
document class can be used and to explain some of its core features.
\end{leporellobox}
\end{leporellocolumn}
\begin{leporellocolumn}{example-b}
\begin{leporellobox}[
  background color={black!10},
  offset={omm,75mm},
  height={\leporellolayoutheight-75mm},
  bleed={r,b},
  name={box-b},
  flow into={box-c}
]
Some more text
\end{leporellobox}
\end{leporellocolumn}
\begin{leporellocolumn}{example-c}
\begin{leporellobox}[
  background color={black!10},
  bleed={l,t},
  name={box-c}
1
\end{leporellobox}
\end{leporellocolumn}
\begin{document}
\leporellotypesetcolumns{
  example-c, example-a, example-b
\end{document}
```

This example shows some features of the flow mechanism. The text in the second box is moved to the end of the collected contents of all three boxes that are connected via the box/flow into and box/name keys. Note that the contents are appended without adding anything between, which is why a \par was added in this example. This example further shows how the command \leporelloboxbreak can be used to ensure that text that flows across boxes with different width is typeset correctly.

9 L3 commands

9.1 L3 package commands

```
\l_leporello_layout_width_dim
\l_leporello_layout_height_dim
```

These variables hold the width and height of the layout which is the width and the height of the final printed matter without info area.

```
\l_leporello_paper_width_dim
\l_leporello_paper_height_dim
```

These variables hold the width and height of the paper including info area.

```
\l_leporello_bleed_dim
\l_leporello_info_area_dim
```

These variables hold the size of the bleed and the info area.

```
\l_leporello_columns_clist
```

This variable holds the list of dimensions that represent the widths of the columns in the layout.

```
\l_leporello_column_count_int
```

This variable holds the number of columns in the layout. It is calculated from the list of dimensions given to the global/columns key.

```
\l_leporello_prepress_bool
\l_leporello_show_frames_bool
\l_leporello_show_id_bool
\l_leporello_auto_typeset_bool
```

These variables hold the relevant values of the global/prepress, global/show frames, global/show id and global/auto typeset keys.

```
\l_leporello_typeset_reverse_layout_bool
\l_leporello_typeset_reverse_order_bool
\l_leporello_typeset_reverse_pagination_bool
\l_leporello_typeset_alternate_layout_bool
\l_leporello_typeset_continuous_pagination_bool
```

These variables hold the relevant values of the typeset/reverse layout, typeset/reverse order, typeset/reverse pagination, typeset/alternate layout and typeset/continuous pagination keys.

```
\l_leporello_layout_vertical_ltr_bool
\l_leporello_layout_vertical_rtl_bool
```

These variables are set to true if the current layout is set to vertical and left-to-right or to vertical and right-to-left.

```
\g_leporello_current_sheet_int
\g_leporello_current_page_int
```

These variables hold the IDs of the current sheet (page in the PDF file) and the current page. A page is considered a column in the document. Pagination is not necessarily continuous. These values are always set globally.

```
\l_leporello_current_column_int
\l_leporello_current_box_int
```

These variables hold the IDs of the current column (column on the sheet) and the current box as integer respectively.

```
\l_leporello_current_column_str
```

This variable holds the name of the current column.

```
\l_leporello_image_width_dim
\l_leporello_image_height_dim
\l_leporello_image_clip_width_dim
\l_leporello_image_clip_height_dim
\l_leporello_image_scale_fp
\l_leporello_image_fill_bleed_bool
```

These variables hold the relevant values of the image/width, image/height, image/clip width, image/clip height, image/scale and image/fill bleed keys.

```
\g_leporello_notes_int
```

This variable holds the current counter for notes.

```
\l_leporello_notes_list_style_str
```

This variable holds the name of the environment of the notes list. It can be changed via the key notes/list style.

```
\leporello_typeset_image:nn {<key-value list>} {<file>}
```

This command typesets the image from the relevant file using the options set via image/keys.

```
\leporello_typeset_columns:nn {<key-value list>} {list of strings>}
\leporello_typeset_columns:nV {<key-value list>} <cli>t varliable>
```

This command is the equivalent of the user-level command \leporellotypesetcolumns. It takes as first argument options set via typeset/ keys and as second argument a list of strings consisting of the names of the columns to be typeset.

```
\leporello_fp_tuple_use_i:n {<fp tuple>}
\leporello_fp_tuple_use_i:e {<fp tuple>}
\leporello_fp_tuple_use_ii:n {<fp tuple>}
\leporello_fp_tuple_use_ii:e {<fp tuple>}
```

These commands extract the first or the second item of a floating point tuple.

```
\leporello_note_mark:n {<integer>}
```

This command expects as argument the value of the current note counter as integer and typesets a corresponding mark. It can be changed via the key notes/mark cmd. The default definition is as follows:

```
_new:Npn \leporello_note_mark:n #1 {
   \leporello_text_superscript:n { \int_use:N #1 }
}
```

9.2 L3 compatibility commands

The following commands have been defined for consistency of the syntax. They are mostly aliases of TeX, LaTeX or LuaTeX commands or token variables or shorthands for setting these.

```
\l_leporello_tex_baselineskip_tl
\l_leporello_tex_pagegoal_tl
\l_leporello_tex_pagetotal_tl
```

These token variables are aliases for \baselikeskip, \pagegoal and \pagetotal.

These commands set the relevant TeX dimension to the argument given. To give an example, \leporello_tex_hoffset_set:n { 1in } sets \hoffset to Iin. Each of these commands also has a ... _gset:n and a ... _add:n variant as well as a ... _zero: variant.

```
\leporello_tex_topskip_zero:
\leporello_tex_parfillskip_zero:
```

These commands set the relevant TeX skip to zero.

```
\leporello_tex_penalty_set:n {<integer>}
```

This command is an alias for \penalty. For example, \leporello_tex_penalty_set:n { -10000 } is equivalent to \penalty -10000.

```
\leporello_tex_par:
```

This command is an alias for \par.

```
\leporello_latex_paperwidth_set:n {<dimension>}
\leporello_latex_paperheight_set:n {<dimension>}
\leporello_latex_textwidth_set:n {<dimension>}
\leporello_latex_textheight_set:n {<dimension>}
\leporello_latex_topmargin_set:n {<dimension>}
\leporello_latex_oddsidemargin_set:n {<dimension>}
\leporello_latex_evensidemargin_set:n {<dimension>}
\leporello_latex_linewidth_set:n {<dimension>}
\leporello_latex_colht_set:n {<dimension>}
```

These commands set the relevant LaTeX dimension to the argument given. Each of these commands also has a \dots gset:n variant. The command

\leporello_latex_colht_set:n sets \@colht.

```
\leporello_latex_headheight_zero: {<dimension>}
\leporello_latex_headsep_zero: {<dimension>}
\leporello_latex_footskip_zero: {<dimension>}
\leporello_latex_marginparwidth_zero: {<dimension>}
\leporello_latex_marginparsep_zero: {<dimension>}
\leporello_latex_marginparpush_zero: {<dimension>}
```

These commands set the relevant LaTeX dimension to zero.

```
\l_leporello_luatex_bodydirection_tl
```

This token variable is an alias for \bodydirection. If LuaTeX is not used, it is empty.

```
\leporello_luatex_pagedir_set:n {<token list>}
\leporello_luatex_bodydir_set:n {<token list>}
\leporello_luatex_pardir_set:n {<token list>}
\leporello_luatex_textdir_set:n {<token list>}
```

These commands are aliases for the relevant LuaTeX commands. For example \leporello_luatex_pagedir_set:n { TLT } is equivalent to \pagedir TLT.

```
\leporello_clearpage:
```

This command is an alias for \clearpage.

```
\leporello_pagestyle_set:n {<string>}
```

The command \leporello_pagestyle_gset:n {#1} is a wrapper for \pagestyle{#1} to set the page style.

```
\leporello_page_gset:n {<integer>}
```

The command \leporello_page_gset:n {#1} is a wrapper for \setcounter{page}{#1} to set the current page number.

```
\leporello_text_superscript:n {<token list>}
```

The command \leporello_text_superscript:n {#1} is a wrapper for #1.

```
\leoprello_graphics_use:nn {<key-value list>} {<file>}
```

The command \leoprello_graphics_use:nn {#1} {#2} is a wrapper for \includegraphics[#1]{#2}.

10 Changes

- **v0.7.0** (2025/08/08) First public beta release.
- **v0.8.0** (2025/08/12) Added box attachment mechanism and option to place arbitrary code to box background.
- **v0.9.0** (2025/08/15) Box attachment mechanism and flow mechanism use box name instead of ID. Enhanced pagination settings. Support for right-to-left and vertical typesetting.
- v0.9.2 (2025/08/18) Various improvements and bug fixes.
- v0.9.3 (2025/08/22) Stretch mechanism fixed.
- v0.9.5 (2025/08/25) Improved alignment mechanism.
- v1.0.0 (2025/08/27) Improved key management and flow mechanism. Added note mechanism.
- v1.0.1 (2025/08/30) Fix of a bug that prevented the dimensions set with the keys store width and store height from having the correct value when used as value to the offset key. Fix of a bug in the stretch mechanism. Fix of a bug in right-to-left typesetting.
- **v1.0.2** (2025/09/10) Documented L3 commands. Fundamental revision of the flow mechanism using the shipout mechanism of LaTeX.
- **v1.0.3** (2025/09/15) Fix of a bug that resulted in wrong size of boxes using the flow mechanism. Added example to documentation to explain flow mechanism.