Package 'fitDTVARMxID'

October 16, 2025
Title Fit the Discrete-Time Vector Autoregressive Model for Multiple Individuals
Version 0.0.0.9000
Description Fit the discrete-time vector autoregressive model for multiple individuals using the 'OpenMx' package (Hunter, 2017 <doi:10.1080 10705511.2017.1369354="">).</doi:10.1080>
<pre>URL https://github.com/jeksterslab/fitDTVARMxID,</pre>
https://jeksterslab.github.io/fitDTVARMxID/
BugReports https://github.com/jeksterslab/fitDTVARMxID/issues
License MIT + file LICENSE
Encoding UTF-8
Roxygen list(markdown = TRUE)
VignetteBuilder knitr
Depends R (>= 4.5.0), OpenMx (>= 2.22.9)
Imports stats, methods, Matrix
Suggests knitr, rmarkdown, testthat, simStateSpace
RoxygenNote 7.3.3.9000
NeedsCompilation no
Author Ivan Jacob Agaloos Pesigan [aut, cre, cph] (ORCID: https://orcid.org/0000-0003-4818-8420)
Maintainer Ivan Jacob Agaloos Pesigan <r.jeksterslab@gmail.com></r.jeksterslab@gmail.com>
Contents
coef.dtvarmxid 2 converged 3 FitDTVARMxID 4 LDL 1 print.dtvarmxid 1 Softplus 1 summary.dtvarmxid 1 vcov.dtvarmxid 1

2 coef.dtvarmxid

Index 18

coef.dtvarmxid	Parameter Estimates	
----------------	---------------------	--

Description

Parameter Estimates

Usage

```
## S3 method for class 'dtvarmxid'
coef(
  object,
  alpha = TRUE,
  beta = TRUE,
  nu = TRUE,
  psi = TRUE,
  theta = TRUE,
  converged = TRUE,
  grad_tol = 0.01,
  hess_tol = 1e-08,
  vanishing_theta = TRUE,
  theta_tol = 0.001,
  ...
)
```

object	Object of class dtvarmxid.
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
beta	Logical. If beta = TRUE, include estimates of the beta matrix, if available. If beta = FALSE, exclude estimates of the beta matrix.
nu	Logical. If nu = TRUE, include estimates of the nu vector, if available. If nu = FALSE, exclude estimates of the nu vector.
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.
converged	Logical. Only include converged cases.
grad_tol	Numeric scalar. Tolerance for the maximum absolute gradient if converged = TRUE.
hess_tol	Numeric scalar. Tolerance for Hessian eigenvalues; eigenvalues must be strictly greater than this value if converged = TRUE.

converged 3

```
vanishing_theta
```

Logical. Test for measurement error variance going to zero if converged =

TRUE.

theta_tol Numeric. Tolerance for vanishing theta test if converged and theta_tol are

TRUE.

... additional arguments.

Value

Returns a list of vectors of parameter estimates.

Author(s)

Ivan Jacob Agaloos Pesigan

converged

Check Model Convergence

Description

Evaluate whether OpenMx fit has converged successfully.

Usage

```
converged(object, ...)
## S3 method for class 'dtvarmxid'
converged(
  object,
  grad_tol = 0.01,
  hess_tol = 1e-08,
  vanishing_theta = TRUE,
  theta_tol = 0.001,
  prop = FALSE,
  ...
)
```

Arguments

object An object of class dtvarmxid.

... Passed to and/or used by methods.

grad_tol Numeric scalar. Tolerance for the maximum absolute gradient.

hess_tol Numeric scalar. Tolerance for Hessian eigenvalues; eigenvalues must be strictly

greater than this value.

vanishing_theta

Logical. Test for measurement error variance going to zero.

theta_tol Numeric. Tolerance for vanishing theta test.

prop Logical. If prop = FALSE, a named logical vector indicating, for each individual fit, whether the convergence criteria are met. If prop = TRUE, the proportion of cases that converged.

Details

Convergence is defined by three criteria:

- 1. Status code equals 0L.
- 2. The maximum absolute gradient is below grad_tol.
- 3. The Hessian is positive definite with all eigenvalues greater than hess_tol.
- 4. If vanishing_theta = TRUE, the model additionally checks that the diagonal elements of the measurement error covariance matrix (Θ) are not vanishingly small, where "small" is defined by theta_tol.

Value

For the dtvarmxid method: If prop = FALSE, a named logical vector indicating, for each individual fit, whether the convergence criteria are met. If prop = TRUE, the proportion of cases that converged.

Author(s)

Ivan Jacob Agaloos Pesigan

FitDTVARMxID

Fit the First-Order Discrete-Time Vector Autoregressive Model by ID

Description

The function fits the first-order discrete-time vector autoregressive model for each unit ID.

Usage

```
FitDTVARMxID(
   data,
   observed,
   id,
   alpha_fixed = TRUE,
   alpha_free = NULL,
   alpha_values = NULL,
   alpha_ubound = NULL,
   alpha_ubound = NULL,
   beta_fixed = FALSE,
   beta_free = NULL,
   beta_values = NULL,
   beta_lbound = NULL,
```

```
beta_ubound = NULL,
psi_diag = FALSE,
psi_d_free = NULL,
psi_d_values = NULL,
psi_d_1bound = NULL,
psi_d_ubound = NULL,
psi_l_free = NULL,
psi_l_values = NULL,
psi_l=1_lbound = NULL,
psi_l_ubound = NULL,
nu_fixed = FALSE,
nu_free = NULL,
nu_values = NULL,
nu_1bound = NULL,
nu_ubound = NULL,
theta_diag = TRUE,
theta_fixed = FALSE,
theta_d_free = NULL,
theta_d_values = NULL,
theta_d_lbound = NULL,
theta_d_ubound = NULL,
theta_d_equal = FALSE,
theta_l_free = NULL,
theta_l_values = NULL,
theta_l_lbound = NULL,
theta_1_ubound = NULL,
mu0_fixed = TRUE,
mu0_func = FALSE,
mu0_free = NULL,
mu0_values = NULL,
mu0_1bound = NULL,
mu0\_ubound = NULL,
sigma0_fixed = TRUE,
sigma0_func = FALSE,
sigma0_diag = FALSE,
sigma0_d_free = NULL,
sigma0_d_values = NULL,
sigma0_d_lbound = NULL,
sigma0_d_ubound = NULL,
sigma0_l_free = NULL,
sigma0_l_values = NULL,
sigma0_l_lbound = NULL,
sigma0_1_ubound = NULL,
tries_explore = 100,
tries_local = 10,
max_attempts = 10,
grad_tol = 0.01,
hess_{tol} = 1e-08,
```

```
eps = 1e-06,
factor = 10,
overwrite = FALSE,
path = getwd(),
prefix = "FitDTVARMxID",
seed = 42,
quiet = FALSE,
ncores = NULL,
clean = TRUE
)
```

data	Data frame. A data frame object of data for potentially multiple subjects that contain a column of subject ID numbers (i.e., an ID variable), and at least one column of observed values.
observed	Character vector. A vector of character strings of the names of the observed variables in the data.
id	Character string. A character string of the name of the ID variable in the data.
alpha_fixed	Logical. If TRUE, the dynamic model intercept vector alpha is fixed. If FALSE, alpha is estimated.
alpha_free	Logical vector indicating which elements of alpha are freely estimated. If NULL, all elements are free. Ignored if alpha_fixed = TRUE.
alpha_values	Numeric vector of values for alpha. If alpha_fixed = TRUE, these are fixed values. If alpha_fixed = FALSE, these are starting values. If NULL, defaults to a vector of zeros.
alpha_lbound	Numeric vector of lower bounds for alpha. If NULL, no lower bounds are set. Ignored if alpha_fixed = TRUE.
alpha_ubound	Numeric vector of upper bounds for alpha. If NULL, no upper bounds are set. Ignored if alpha_fixed = TRUE.
beta_fixed	Logical. If TRUE, the dynamic model coefficient matrix beta is fixed. If FALSE, beta is estimated.
beta_free	Logical matrix indicating which elements of beta are freely estimated. If NULL, all elements are free. Ignored if beta_fixed = TRUE.
beta_values	Numeric matrix of values for beta. If beta_fixed = TRUE, these are fixed values. If beta_fixed = FALSE, these are starting values. If NULL, defaults to a zero matrix.
beta_lbound	Numeric matrix of lower bounds for beta. If NULL, defaults to -1.5. Ignored if $beta_fixed = TRUE$.
beta_ubound	Numeric matrix of upper bounds for beta. If NULL, defaults to $+1.5$. Ignored if beta_fixed = TRUE.
psi_diag	Logical. If TRUE, psi is diagonal. If FALSE, psi is symmetric.
psi_d_free	$Logical\ vector\ indicating\ free/fixed\ status\ of\ the\ elements\ of\ psi_d.\ If\ NULL,\ all\ element\ of\ psi_d\ are\ free.$

psi_d_values	Numeric vector with starting values for psi_d. If NULL, defaults to a vector of ones.
psi_d_lbound	Numeric vector with lower bounds for psi_d. If NULL, no lower bounds are set.
psi_d_ubound	Numeric vector with upper bounds for psi_d. If NULL, no upper bounds are set.
psi_l_free	Logical matrix indicating which strictly-lower-triangular elements of psi_l are free. Ignored if psi_diag = TRUE.
psi_l_values	Numeric matrix of starting values for the strictly-lower-triangular elements of psi_1. If NULL, defaults to a null matrix.
psi_l_lbound	Numeric matrix with lower bounds for psi_1. If NULL, no lower bounds are set.
psi_l_ubound	Numeric matrix with upper bounds for psi_1. If NULL, no upper bounds are set.
nu_fixed	Logical. If TRUE, the measurement model intercept vector nu is fixed. If FALSE, nu is estimated.
nu_free	Logical vector indicating which elements of nu are freely estimated. If NULL, all elements are free. Ignored if nu_fixed = TRUE.
nu_values	Numeric vector of values for nu. If nu_fixed = TRUE, these are fixed values. If nu_fixed = FALSE, these are starting values. If NULL, defaults to a vector of zeros.
nu_1bound	Numeric vector of lower bounds for nu. If NULL, no lower bounds are set. Ignored if nu_fixed = TRUE.
nu_ubound	Numeric vector of upper bounds for nu. If NULL, no upper bounds are set. Ignored if nu_fixed = TRUE.
theta_diag	Logical If TDUE that a is diagonal If EALSE that a is symmetric
the ta_arag	Logical. If TRUE, theta is diagonal. If FALSE, theta is symmetric.
theta_fixed	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero).
_	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values).
theta_fixed theta_d_free	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero). Logical vector indicating free/fixed status of the diagonal parameters theta_d.
theta_fixed theta_d_free theta_d_values	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero). Logical vector indicating free/fixed status of the diagonal parameters theta_d. If NULL, all element of theta_d are free. Numeric vector with starting values for theta_d. If theta_fixed = TRUE, these are fixed values. If theta_fixed = FALSE, these are starting values. If NULL,
theta_fixed theta_d_free theta_d_values theta_d_lbound	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero). Logical vector indicating free/fixed status of the diagonal parameters theta_d. If NULL, all element of theta_d are free. Numeric vector with starting values for theta_d. If theta_fixed = TRUE, these are fixed values. If theta_fixed = FALSE, these are starting values. If NULL, defaults to an identity matrix. Numeric vector with lower bounds for theta_d. If NULL, no lower bounds are
theta_fixed theta_d_free theta_d_values theta_d_lbound	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero). Logical vector indicating free/fixed status of the diagonal parameters theta_d. If NULL, all element of theta_d are free. Numeric vector with starting values for theta_d. If theta_fixed = TRUE, these are fixed values. If theta_fixed = FALSE, these are starting values. If NULL, defaults to an identity matrix. Numeric vector with lower bounds for theta_d. If NULL, no lower bounds are set. Numeric vector with upper bounds for theta_d. If NULL, no upper bounds are
theta_fixed theta_d_free theta_d_values theta_d_lbound theta_d_ubound	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero). Logical vector indicating free/fixed status of the diagonal parameters theta_d. If NULL, all element of theta_d are free. Numeric vector with starting values for theta_d. If theta_fixed = TRUE, these are fixed values. If theta_fixed = FALSE, these are starting values. If NULL, defaults to an identity matrix. Numeric vector with lower bounds for theta_d. If NULL, no lower bounds are set. Numeric vector with upper bounds for theta_d. If NULL, no upper bounds are set. Logical. When TRUE, all free diagonal elements of theta_d are constrained to be equal and estimated as a single shared parameter (theta_eq). Ignored if no
theta_fixed theta_d_free theta_d_values theta_d_lbound theta_d_ubound theta_d_equal theta_l_free	Logical. If TRUE, the measurement error matrix theta is fixed to SoftPlus(theta_d_values). If FALSE, only diagonal elements are estimated (off-diagonals fixed to zero). Logical vector indicating free/fixed status of the diagonal parameters theta_d. If NULL, all element of theta_d are free. Numeric vector with starting values for theta_d. If theta_fixed = TRUE, these are fixed values. If theta_fixed = FALSE, these are starting values. If NULL, defaults to an identity matrix. Numeric vector with lower bounds for theta_d. If NULL, no lower bounds are set. Numeric vector with upper bounds for theta_d. If NULL, no upper bounds are set. Logical. When TRUE, all free diagonal elements of theta_d are constrained to be equal and estimated as a single shared parameter (theta_eq). Ignored if no diagonal elements are free. Logical matrix indicating which strictly-lower-triangular elements of theta_1

set.

theta_l_ubound	Numeric matrix with upper bounds for theta_1. If NULL, no upper bounds are set.
mu0_fixed	Logical. If TRUE, the initial mean vector mu0 is fixed. If FALSE, mu0 is estimated.
mu0_func	Logical. If TRUE and mu0_fixed = TRUE, mu0 is fixed to $(I - \beta)^{-1}\alpha$.
mu0_free	Logical vector indicating which elements of mu0 are freely estimated.
mu0_values	Numeric vector of values for mu0. If mu0_fixed = TRUE, these are fixed values. If mu0_fixed = FALSE, these are starting values. If NULL, defaults to a vector of zeros.
mu0_lbound	Numeric vector of lower bounds for mu0. If NULL, no lower bounds are set. Ignored if mu0_fixed = TRUE.
mu0_ubound	Numeric vector of upper bounds for mu0. If NULL, no upper bounds are set. Ignored if mu0_fixed = TRUE.
sigma0_fixed	Logical. If TRUE, the initial covariance matrix sigma0 is fixed. If FALSE, sigma0 is estimated.
sigma0_func	Logical. If TRUE and sigma0_fixed = TRUE, sigma0 is fixed to $(I-\beta\otimes\beta)^{-1}\mathrm{Vec}(\Psi)$.
sigma0_diag	Logical. If TRUE, sigma0 is diagonal. If FALSE, sigma0 is symmetric.
sigma0_d_free	Logical vector indicating free/fixed status of the elements of sigma0_d. If NULL, all element of sigma0_d are free.
sigma0_d_value	
	Numeric vector with starting values for sigma@_d. If NULL, defaults to a vector of ones.
sigma0_d_lbound	
	Numeric vector with lower bounds for sigma@_d. If NULL, no lower bounds are set.
sigma0_d_ubound	Numeric vector with upper bounds for sigma0_d. If NULL, no upper bounds are
	set.
sigma0_l_free	Logical matrix indicating which strictly-lower-triangular elements of sigma0_l are free. Ignored if sigma0_diag = TRUE.
sigma0_l_value	
	Numeric matrix of starting values for the strictly-lower-triangular elements of sigma0_1. If NULL, defaults to a null matrix.
sigma0_l_lbound	
	Numeric matrix with lower bounds for sigma@_1. If NULL, no lower bounds are set.
sigma0_l_ubound	
	Numeric matrix with upper bounds for sigma0_1. If NULL, no upper bounds are set.
tries_explore	Integer. Number of extra tries for the wide exploration phase using OpenMx::mxTryHardWideSearch() with checkHess = FALSE.
tries_local	Integer. Number of extra tries for local polishing via OpenMx::mxTryHard() when gradients remain above tolerance.
max_attempts	Integer. Maximum number of remediation attempts after the first Hessian computation fails the criteria. Each attempt may nudge off bounds, refit locally without the Hessian and on the last attempt, relay bounds.

without the Hessian, and, on the last attempt, relax bounds.

grad_tol	Numeric. Tolerance for the maximum absolute gradient. Smaller values are stricter.
hess_tol	Numeric. Minimum allowable Hessian eigenvalue. Smaller values are less strict.
eps	Numeric. Proximity threshold to detect parameters on their bounds and to nudge them inward by $10 * eps$.
factor	Numeric. Multiplicative factor to relax parameter bounds on the final remediation attempt. Lower bounds are divided by factor and upper bounds are multiplied by factor.
overwrite	Logical. If TRUE, existing intermediate files are overwritten. Defaults to FALSE.
path	Character string. Directory in which to save intermediate files.
prefix	Alphanumeric character string. Prefix to use when naming intermediate files.
seed	Random seed for reproducibility.
quiet	Logical. If TRUE, suppresses messages during the model fitting stage.
ncores	Positive integer. Number of cores to use.
clean	Logical. If TRUE, clean intermediate files saved in path.

Details

The measurement model is given by

$$\mathbf{y}_{i,t} = \mathbf{\nu} + \mathbf{\Lambda} \boldsymbol{\eta}_{i,t} + \boldsymbol{\varepsilon}_{i,t}, \quad ext{with} \quad \boldsymbol{\varepsilon}_{i,t} \sim \mathcal{N}\left(\mathbf{0}, \mathbf{\Theta}\right)$$

where $\mathbf{y}_{i,t}$, $\boldsymbol{\eta}_{i,t}$, and $\boldsymbol{\varepsilon}_{i,t}$ are random variables and $\boldsymbol{\nu}$, $\boldsymbol{\Lambda}$, and $\boldsymbol{\Theta}$ are model parameters. $\mathbf{y}_{i,t}$ represents a vector of observed random variables, $\boldsymbol{\eta}_{i,t}$ a vector of latent random variables, and $\boldsymbol{\varepsilon}_{i,t}$ a vector of random measurement errors, at time t and individual i. $\boldsymbol{\Lambda}$ denotes a matrix of factor loadings, and $\boldsymbol{\Theta}$ the covariance matrix of $\boldsymbol{\varepsilon}$. In this model, $\boldsymbol{\Lambda}$ is an identity matrix and $\boldsymbol{\Theta}$ is a diagonal matrix.

The dynamic structure is given by

$$oldsymbol{\eta}_{i,t} = oldsymbol{lpha} + oldsymbol{eta} oldsymbol{\eta}_{i,t-1} + oldsymbol{\zeta}_{i,t}, \quad ext{with} \quad oldsymbol{\zeta}_{i,t} \sim \mathcal{N}\left(oldsymbol{0}, oldsymbol{\Psi}
ight)$$

where $\eta_{i,t}$, $\eta_{i,t-1}$, and $\zeta_{i,t}$ are random variables, and α , β , and Ψ are model parameters. Here, $\eta_{i,t}$ is a vector of latent variables at time t and individual i, $\eta_{i,t-1}$ represents a vector of latent variables at time t-1 and individual i, and $\zeta_{i,t}$ represents a vector of dynamic noise at time t and individual i. α denotes a vector of intercepts, β a matrix of autoregression and cross regression coefficients, and Ψ the covariance matrix of $\zeta_{i,t}$.

Value

Returns an object of class dtvarmxid which is a list with the following elements:

call Function call.

args List of function arguments.

fun Function used ("FitDTVARMxID").

output A list of fitted OpenMx models.

Author(s)

Ivan Jacob Agaloos Pesigan

References

Hunter, M. D. (2017). State space modeling in an open source, modular, structural equation modeling environment. *Structural Equation Modeling: A Multidisciplinary Journal*, 25(2), 307–324. doi:10.1080/10705511.2017.1369354

Neale, M. C., Hunter, M. D., Pritikin, J. N., Zahery, M., Brick, T. R., Kirkpatrick, R. M., Estabrook, R., Bates, T. C., Maes, H. H., & Boker, S. M. (2015). OpenMx 2.0: Extended structural equation and statistical modeling. *Psychometrika*, *81*(2), 535–549. doi:10.1007/s1133601494358

See Also

Other DTVAR Functions: LDL(), Softplus()

Examples

```
## Not run:
# Generate data using the simStateSpace package------
set.seed(42)
k <- 2
n <- 5
time <- 100
alpha < - rep(x = 0, times = k)
beta <- matrix(</pre>
  data = c(.5, .0, .2, .5),
 nrow = k,
 ncol = k
)
psi <- matrix(</pre>
  data = c(exp(-4.1), exp(-3.9), exp(-3.9), exp(-3.2)),
  nrow = k,
 ncol = k
psi_l <- t(chol(psi))</pre>
nu \leftarrow rep(x = 5, times = k)
lambda <- diag(k)</pre>
theta <- matrix(</pre>
  data = c(exp(-2), 0, 0, exp(-2.8)),
 nrow = k,
 ncol = k
theta_l <- t(chol(theta))</pre>
mu0 <- c(solve(diag(k) - beta) %*% alpha)</pre>
sigma0 <- matrix(</pre>
  data = c(
    solve(diag(k * k) - beta %x% beta) %*% c(psi)
  ),
  nrow = k,
  ncol = k
```

LDL 11

```
sigma0_l <- t(chol(sigma0))</pre>
sim <- simStateSpace::SimSSMIVary(</pre>
 n = n,
 time,
 mu0 = list(mu0),
 sigma0_l = list(sigma0_l),
 alpha = list(alpha),
 beta = simStateSpace::SimBetaN(
   n = n,
   beta = beta,
   vcov_beta_vec_l = t(chol(0.1 * diag(k * k)))
 ),
 psi_l = list(psi_l),
 nu = list(nu),
 lambda = list(lambda),
 theta_l = list(theta_l)
)
data <- as.data.frame(sim)</pre>
# Fit the model------
library(fitDTVARMxID)
fit <- FitDTVARMxID(</pre>
 data = data,
 observed = paste0("y", seq_len(k)),
 id = "id"
print(fit)
summary(fit)
coef(fit)
vcov(fit)
converged(fit)
## End(Not run)
```

LDL

LDL' Decomposition of a Symmetric Positive-Definite Matrix

Description

Performs an LDL' factorization of a symmetric positive-definite matrix X, such that

$$X = LDL^{\top},$$

where L is unit lower-triangular (ones on the diagonal) and D is diagonal.

Usage

LDL(x)

12 print.dtvarmxid

Arguments

Χ

Numeric matrix. Must be symmetric positive-definite.

Details

This function returns both the unit lower-triangular factor L and the diagonal factor D. The strictly lower-triangular part of L is also provided for convenience. The function additionally computes an unconstrained vector d_uc such that $softplus(d_uc) = d_vec$, using $softplus^{-1}(y) = log(exp(y) - 1)$ for stable back-transformation.

Value

A list with components:

```
1_mat_unit
                  Unit lower-triangular matrix L.
1_mat_strict
                  Strictly lower-triangular part of L.
d_mat
                  Diagonal matrix D.
d_vec
                  Vector of diagonal entries of D.
                  Unconstrained vector with softplus(d_uc) = d_vec.
d_uc
Х
                  Original input matrix.
                  Reconstructed matrix LDL^{\top}.
У
diff
                  Difference x - y.
```

See Also

```
Other DTVAR Functions: FitDTVARMxID(), Softplus()
```

Examples

```
set.seed(123)
A <- matrix(rnorm(16), 4, 4)
S <- crossprod(A) + diag(1e-6, 4) # SPD
out <- LDL(S)
max(abs(out$diff))</pre>
```

print.dtvarmxid

Print Method for Object of Class dtvarmxid

Description

Print Method for Object of Class dtvarmxid

print.dtvarmxid 13

Usage

```
## S3 method for class 'dtvarmxid'
print(
    x,
    means = FALSE,
    alpha = TRUE,
    beta = TRUE,
    nu = TRUE,
    psi = TRUE,
    theta = TRUE,
    converged = TRUE,
    grad_tol = 0.01,
    hess_tol = 1e-08,
    vanishing_theta = TRUE,
    theta_tol = 0.001,
    ...
)
```

x	an object of class dtvarmxid.
means	$\label{eq:Logical} \mbox{Logical. If means = TRUE, return means. Otherwise, the function returns raw estimates.}$
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
beta	$Logical. \ If \ beta = \ TRUE, \ include \ estimates \ of \ the \ beta \ matrix, \ if \ available. \ If \ beta = \ FALSE, \ exclude \ estimates \ of \ the \ beta \ matrix.$
nu	Logical. If $nu = TRUE$, include estimates of the nu vector, if available. If $nu = FALSE$, exclude estimates of the nu vector.
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.
theta	$Logical.\ If\ the \verb ta=TRUE ,\ include\ estimates\ of\ the\ the \verb ta=matrix ,\ if\ available.\ If\ the \verb ta=FALSE ,\ exclude\ estimates\ of\ the\ the \verb ta=matrix .$
converged	Logical. Only include converged cases.
grad_tol	Numeric scalar. Tolerance for the maximum absolute gradient if converged = $TRUE$.
hess_tol	Numeric scalar. Tolerance for Hessian eigenvalues; eigenvalues must be strictly greater than this value if converged = TRUE.
vanishing_theta	
	Logical. Test for measurement error variance going to zero if converged = TRUE.
theta_tol	Numeric. Tolerance for vanishing theta test if converged and theta_tol are TRUE.
	further arguments.

Softplus Softplus

Author(s)

Ivan Jacob Agaloos Pesigan

Softplus

Softplus and Inverse Softplus Transformations

Description

The softplus transformation maps unconstrained real values to the positive real line. This is useful when parameters (e.g., variances) must be strictly positive. The inverse softplus transformation recovers the unconstrained value from a positive input.

Usage

```
Softplus(x)
InvSoftplus(x)
```

Arguments

x Numeric vector

Numeric vector or matrix. Input values to be transformed.

Details

- Softplus(x) = log(1 + exp(x))
- InvSoftplus(x) = log(exp(x) 1)

For numerical stability, these functions use log1p() and expm1() internally.

Value

- Softplus(): numeric vector or matrix of strictly positive values.
- InvSoftplus(): numeric vector or matrix of unconstrained values.

Author(s)

Ivan Jacob Agaloos Pesigan

See Also

```
Other DTVAR Functions: FitDTVARMxID(), LDL()
```

summary.dtvarmxid 15

Examples

```
# Apply softplus to unconstrained values
x <- c(-5, 0, 5)
y <- Softplus(x)

# Recover unconstrained values
x_recovered <- InvSoftplus(y)

y
x_recovered</pre>
```

summary.dtvarmxid

Summary Method for Object of Class dtvarmxid

Description

Summary Method for Object of Class dtvarmxid

Usage

```
## S3 method for class 'dtvarmxid'
summary(
   object,
   means = FALSE,
   alpha = TRUE,
   beta = TRUE,
   nu = TRUE,
   psi = TRUE,
   theta = TRUE,
   converged = TRUE,
   grad_tol = 0.01,
   hess_tol = 1e-08,
   vanishing_theta = TRUE,
   theta_tol = 0.001,
   ...
)
```

object	an object of class dtvarmxid.
means	Logical. If means = TRUE, return means. Otherwise, the function returns raw estimates.
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.
beta	Logical. If beta = TRUE, include estimates of the beta matrix, if available. If beta = FALSE, exclude estimates of the beta matrix.

16 vcov.dtvarmxid

nu	Logical. If nu = TRUE, include estimates of the nu vector, if available. If nu = FALSE, exclude estimates of the nu vector.	
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.	
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.	
converged	Logical. Only include converged cases.	
grad_tol	Numeric scalar. Tolerance for the maximum absolute gradient if converged = TRUE.	
hess_tol	Numeric scalar. Tolerance for Hessian eigenvalues; eigenvalues must be strictly greater than this value if converged = TRUE.	
vanishing_theta		
	Logical. Test for measurement error variance going to zero if converged = TRUE.	
theta_tol	Numeric. Tolerance for vanishing theta test if converged and theta_tol are TRUE.	
	further arguments.	

Author(s)

Ivan Jacob Agaloos Pesigan

vcov.dtvarmxid Sampling Covariance Matrix of the Parameter Estimates

Description

Sampling Covariance Matrix of the Parameter Estimates

Usage

```
## S3 method for class 'dtvarmxid'
vcov(
  object,
  alpha = TRUE,
  beta = TRUE,
  nu = TRUE,
  psi = TRUE,
  theta = TRUE,
  converged = TRUE,
  grad_tol = 0.01,
  hess_tol = 1e-08,
  vanishing_theta = TRUE,
  theta_tol = 0.001,
  ...
)
```

vcov.dtvarmxid 17

Arguments

object	Object of class dtvarmxid.	
alpha	Logical. If alpha = TRUE, include estimates of the alpha vector, if available. If alpha = FALSE, exclude estimates of the alpha vector.	
beta	Logical. If beta = TRUE, include estimates of the beta matrix, if available. If beta = FALSE, exclude estimates of the beta matrix.	
nu	Logical. If nu = TRUE, include estimates of the nu vector, if available. If nu = FALSE, exclude estimates of the nu vector.	
psi	Logical. If psi = TRUE, include estimates of the psi matrix, if available. If psi = FALSE, exclude estimates of the psi matrix.	
theta	Logical. If theta = TRUE, include estimates of the theta matrix, if available. If theta = FALSE, exclude estimates of the theta matrix.	
converged	Logical. Only include converged cases.	
grad_tol	Numeric scalar. Tolerance for the maximum absolute gradient if converged = TRUE.	
hess_tol	Numeric scalar. Tolerance for Hessian eigenvalues; eigenvalues must be strictly greater than this value if converged = TRUE.	
vanishing_theta		
	Logical. Test for measurement error variance going to zero if converged = TRUE.	
theta_tol	Numeric. Tolerance for vanishing theta test if converged and theta_tol are TRUE.	
	additional arguments.	

Value

Returns a list of sampling variance-covariance matrices.

Author(s)

Ivan Jacob Agaloos Pesigan

Index

```
* DTVAR Functions
    FitDTVARMxID, 4
    LDL, 11
    Softplus, 14
*\ \textbf{fitDTVARMxID}
    FitDTVARMxID, 4
    LDL, 11
    Softplus, 14
* fit
    FitDTVARMxID, 4
* methods
    coef.dtvarmxid, 2
    converged, 3
    print.dtvarmxid, 12
    summary.dtvarmxid, 15
    vcov.dtvarmxid, 16
* misc
    LDL, 11
    Softplus, 14
coef.dtvarmxid, 2
FitDTVARMxID, 4, 12, 14
InvSoftplus (Softplus), 14
LDL, 10, 11, 14
print.dtvarmxid, 12
Softplus, 10, 12, 14
summary.dtvarmxid, 15
vcov.dtvarmxid, 16
```