## libhpdftbl

Generated on Mon Apr 25 2022 06:41:42 for libhpdftbl by Doxygen 1.9.3

Mon Apr 25 2022 06:41:42

1 Introduction to hpdftbl	1
1.1 What is this?	1
1.2 Features	1
1.3 Some Examples	2
1.3.1 Example 1 - Plain table with cell labels	2
1.3.2 Example 2 - Table with cell labels	2
1.3.3 Example 2 - Plain table with row/column spanning and table title	3
1.3.4 Example 3 - Table with labels and cell widgets	3
2 Building the library	5
2.1 The short version	5
2.1.1 Compiling the tar ball	5
2.1.2 Compiling after cloning the git repo	5
2.2 Pre-requisites	6
2.3 Different versions of iconv on OSX	6
2.3.1 OSX native libiconv	6
2.3.2 OSX GNU port of libiconv	6
2.3.3 Troubleshooting OSX <tt>libiconv</tt>	7
2.4 Building the library from source	7
2.4.1 Rebuilding using a build environment	7
2.4.2 Rebuilding from the cloned repo	8
2.5 Some notes on Windows build	8
2.6 Using C or C++ to build	8
3 Getting started	g
3.1 Creating a PDF page infrastructure	9
3.2 Your first table	10
3.3 Your second table - disconnecting program structure from data	11
3.4 Adding a header row	12
3.5 Using labels in the table cells	13
3.6 Adding a table title	14
3.7 Adjusting fonts and colors	14
4 Adjusting the layout of the table	15
4.1 Cell and row spanning	15
4.2 Adjusting column width	15
5 Content and label callbacks	17
5.1 Introducing content callback functions	17
5.2 A content callback example	18
6 Error handling	21
6.1 Translating HPDF error codes	22
6.2 Example of setting up error handler	22

7 Style and font setting	23
7.1 Specifying fonts and colors	23
7.2 Using style callbacks	24
7.2.1 Style callback example	25
7.3 Using style themes	26
8 Tables layout from data	29
8.1 Defining a table in data	29
8.2 A first example of defining table as data	30
8.3 A second example of defining a table as data	30
9 Using Widgets	33
10 HPDFTBL API Overview	35
10.1 Table creation related functions	35
10.2 Table error handling	35
10.3 Theme handling methods	35
10.4 Table layout adjusting functions	36
10.5 Table style modifying functions	36
10.6 Content handling	36
10.7 Callback handling	37
10.8 Text encoding	37
10.9 Misc utility function	37
11 Data Structure Index	39
11.1 Data Structures	39
12 File Index	41
12.1 File List	41
13 Data Structure Documentation	43
13.1 border_style Struct Reference	43
13.1.1 Detailed Description	43
13.1.2 Field Documentation	43
13.1.2.1 color	43
13.1.2.2 line_style	43
13.1.2.3 width	44
13.2 hpdftbl Struct Reference	44
13.2.1 Detailed Description	45
13.2.2 Field Documentation	45
13.2.2.1 canvas_cb	45
13.2.2.2 cells	45
13.2.2.3 col_width_percent	45
13.2.2.4 cols	45

13.2.2.5 content_cb	 . 46
13.2.2.6 content_style	 . 46
13.2.2.7 content_style_cb	 . 46
13.2.2.8 header_style	 . 46
13.2.2.9 height	 . 46
13.2.2.10 inner_border	 . 46
13.2.2.11 label_cb	 . 46
13.2.2.12 label_style	 . 47
13.2.2.13 outer_border	 . 47
13.2.2.14 pdf_doc	 . 47
13.2.2.15 pdf_page	 . 47
13.2.2.16 posx	 . 47
13.2.2.17 posy	 . 47
13.2.2.18 rows	 . 47
13.2.2.19 tag	 . 48
13.2.2.20 title_style	 . 48
13.2.2.21 title_txt	 . 48
13.2.2.22 use_cell_labels	 . 48
13.2.2.23 use_header_row	 . 48
13.2.2.24 use_label_grid_style	 . 48
13.2.2.25 width	 . 48
13.3 hpdftbl_cell Struct Reference	 . 49
13.3.1 Detailed Description	 . 49
13.3.2 Field Documentation	 . 49
13.3.2.1 canvas_cb	 . 49
13.3.2.2 colspan	 . 49
13.3.2.3 content	 . 50
13.3.2.4 content_cb	 . 50
13.3.2.5 content_style	 . 50
13.3.2.6 delta_x	 . 50
13.3.2.7 delta_y	 . 50
13.3.2.8 height	 . 50
13.3.2.9 label	 . 50
13.3.2.10 label_cb	 . 50
13.3.2.11 parent_cell	 . 51
13.3.2.12 rowspan	 . 51
13.3.2.13 style_cb	 . 51
13.3.2.14 textwidth	 . 51
13.3.2.15 width	 . 51
13.4 hpdftbl_cell_spec Struct Reference	 . 51
13.4.1 Detailed Description	 . 52
13.4.2 Field Documentation	 . 52

13.4.2.1 canvas_cb	52
13.4.2.2 col	52
13.4.2.3 colspan	52
13.4.2.4 content_cb	53
13.4.2.5 label	53
13.4.2.6 label_cb	53
13.4.2.7 row	53
13.4.2.8 rowspan	53
13.4.2.9 style_cb	53
13.5 hpdftbl_errcode_entry Struct Reference	54
13.5.1 Detailed Description	54
13.5.2 Field Documentation	54
13.5.2.1 errcode	54
13.5.2.2 errstr	54
13.6 hpdftbl_spec Struct Reference	54
13.6.1 Detailed Description	55
13.6.2 Field Documentation	55
13.6.2.1 cell_spec	55
13.6.2.2 cols	55
13.6.2.3 content_cb	56
13.6.2.4 height	56
13.6.2.5 label_cb	56
13.6.2.6 post_cb	56
13.6.2.7 rows	56
13.6.2.8 style_cb	56
13.6.2.9 title	57
13.6.2.10 use_header	57
13.6.2.11 use_labelgrid	57
13.6.2.12 use_labels	57
13.6.2.13 width	57
13.6.2.14 xpos	57
13.6.2.15 ypos	58
13.7 hpdftbl_theme Struct Reference	58
13.7.1 Detailed Description	58
13.7.2 Field Documentation	58
13.7.2.1 content_style	58
13.7.2.2 header_style	59
13.7.2.3 inner_border	59
13.7.2.4 label_style	59
13.7.2.5 outer_border	59
13.7.2.6 title_style	59
13.7.2.7 use_header_row	59

	13.7.2.8 use_label_grid_style	59
	13.7.2.9 use_labels	60
	13.8 line_dash_style Struct Reference	60
	13.8.1 Detailed Description	60
	13.8.2 Field Documentation	60
	13.8.2.1 dash_ptn	60
	13.8.2.2 num	60
	13.9 text_style Struct Reference	61
	13.9.1 Detailed Description	61
	13.9.2 Field Documentation	61
	13.9.2.1 background	61
	13.9.2.2 color	61
	13.9.2.3 font	62
	13.9.2.4 fsize	62
	13.9.2.5 halign	62
4.4	File Documentation	63
14		63
	14.1 config.h	
	14.2 /Users/ljp/Devel/hpdf_table/src/hpdftbl.c File Reference	64
	·	67 67
	14.2.2 Function Documentation	67
	14.2.2.1 HPDF_RoundedCornerRectangle()	
	14.2.2.2 hpdftbl_apply_theme()	68
	14.2.2.3 hpdftbl_clear_spanning()	68
	14.2.2.4 hpdftbl_create()	69
	14.2.2.5 hpdftbl_create_title()	69
	14.2.2.6 hpdftbl_default_table_error_handler()	70
	14.2.2.7 hpdftbl_destroy()	70
	· – •	70
	14.2.2.9 hpdftbl_encoding_text_out()	71 71
	14.2.2.10 hpdftbl get_anchor_top_left()	71 72
	14.2.2.11 hpdftbl _get_default_theme()	
	14.2.2.12 hpdftbl_get_errstr()	72 73
	14.2.2.14 hpdftbl_get_last_errcode()	73
	14.2.2.15 hpdftbl_set_anchor_top_left()	73 73
		73 74
	14.2.2.16 hpdftbl_set_background()	
	. – – – "	74 75
	14.2.2.18 hpdftbl_set_cell()	
	14.2.2.19 hpdftbl_set_cell_canvas_cb()	75 76
	14.2.2.20 hpdftbl_set_cell_content_cb()	76 77
	14.2.2.21 hpdftbl_set_cell_content_style()	77

14.2.2.22 hpdftbl_set_cell_content_style_cb()	77
14.2.2.23 hpdftbl_set_cell_label_cb()	78
14.2.2.24 hpdftbl_set_cellspan()	79
14.2.2.25 hpdftbl_set_col_content_style()	79
14.2.2.26 hpdftbl_set_colwidth_percent()	80
14.2.2.27 hpdftbl_set_content()	80
14.2.2.28 hpdftbl_set_content_cb()	81
14.2.2.29 hpdftbl_set_content_style()	82
14.2.2.30 hpdftbl_set_content_style_cb()	82
14.2.2.31 hpdftbl_set_errhandler()	83
14.2.2.32 hpdftbl_set_header_halign()	83
14.2.2.33 hpdftbl_set_header_style()	84
14.2.2.34 hpdftbl_set_inner_border()	84
14.2.2.35 hpdftbl_set_label_cb()	85
14.2.2.36 hpdftbl_set_label_style()	85
14.2.2.37 hpdftbl_set_labels()	86
14.2.2.38 hpdftbl_set_line_dash()	87
14.2.2.39 hpdftbl_set_outer_border()	87
14.2.2.40 hpdftbl_set_row_content_style()	88
14.2.2.41 hpdftbl_set_tag()	88
14.2.2.42 hpdftbl_set_text_encoding()	89
14.2.2.43 hpdftbl_set_title()	89
14.2.2.44 hpdftbl_set_title_halign()	90
14.2.2.45 hpdftbl_set_title_style()	90
14.2.2.46 hpdftbl_stroke()	91
14.2.2.47 hpdftbl_stroke_from_data()	92
14.2.2.48 hpdftbl_use_header()	92
14.2.2.49 hpdftbl_use_labelgrid()	93
14.2.2.50 hpdftbl_use_labels()	93
14.3 /Users/ljp/Devel/hpdf_table/src/hpdftbl.h File Reference	94
14.3.1 Detailed Description	99
14.3.2 Macro Definition Documentation	99
14.3.2.1 A3PAGE_HEIGHT_CM	99
14.3.2.2 A3PAGE_WIDTH_CM	99
14.3.2.3 A4PAGE_HEIGHT_CM	99
14.3.2.4 A4PAGE_WIDTH_CM	100
14.3.2.5 COLOR_DARK_RED	100
14.3.2.6 HPDF_COLOR_FROMRGB	100
14.3.2.7 HPDF_FF_TIMES	
14.3.2.8 hpdftbl_cm2dpi	100
14.3.2.9 HPDFTBL_DEFAULT_TARGET_ENCODING	101
14.3.2.10 HPDFTBL_END_CELLSPECS	101

14.3.2.11 LEGALPAGE_HEIGHT_CM	. 101
14.3.2.12 LEGALPAGE_WIDTH_CM	. 101
14.3.2.13 LETTERRPAGE_HEIGHT_CM	. 101
14.3.2.14 LETTERRPAGE_WIDTH_CM	102
14.3.2.15 MIN_CALCULATED_PERCENT_CELL_WIDTH	102
14.3.3 Typedef Documentation	102
14.3.3.1 hpdf_border_style_t	102
14.3.3.2 hpdf_text_style_t	102
14.3.3.3 hpdftbl_callback_t	102
14.3.3.4 hpdftbl_canvas_callback_t	103
14.3.3.5 hpdftbl_cell_spec_t	103
14.3.3.6 hpdftbl_cell_t	103
14.3.3.7 hpdftbl_content_callback_t	103
14.3.3.8 hpdftbl_content_style_callback_t	104
14.3.3.9 hpdftbl_error_handler_t	104
14.3.3.10 hpdftbl_spec_t	104
14.3.3.11 hpdftbl_t	104
14.3.3.12 hpdftbl_text_align_t	105
14.3.3.13 hpdftbl_theme_t	105
14.3.4 Enumeration Type Documentation	105
14.3.4.1 hpdftbl_dash_style	105
14.3.4.2 hpdftbl_text_align	105
14.3.5 Function Documentation	106
14.3.5.1 HPDF_RoundedCornerRectangle()	106
14.3.5.2 hpdftbl_apply_theme()	106
14.3.5.3 hpdftbl_clear_spanning()	107
14.3.5.4 hpdftbl_create()	107
14.3.5.5 hpdftbl_create_title()	. 108
14.3.5.6 hpdftbl_default_table_error_handler()	108
14.3.5.7 hpdftbl_destroy()	109
14.3.5.8 hpdftbl_destroy_theme()	109
14.3.5.9 hpdftbl_encoding_text_out()	109
14.3.5.10 hpdftbl_get_anchor_top_left()	. 110
14.3.5.11 hpdftbl_get_default_theme()	. 110
14.3.5.12 hpdftbl_get_errstr()	. 110
14.3.5.13 hpdftbl_get_last_auto_height()	. 111
14.3.5.14 hpdftbl_get_last_errcode()	. 111
14.3.5.15 hpdftbl_hpdf_get_errstr()	. 112
14.3.5.16 hpdftbl_set_anchor_top_left()	. 112
14.3.5.17 hpdftbl_set_background()	. 113
14.3.5.18 hpdftbl_set_canvas_cb()	. 113
14.3.5.19 hpdftbl_set_cell()	. 114

14.3.5.20 hpdftbl_set_cell_canvas_cb()	14
14.3.5.21 hpdftbl_set_cell_content_cb()	15
14.3.5.22 hpdftbl_set_cell_content_style()	16
14.3.5.23 hpdftbl_set_cell_content_style_cb()	16
14.3.5.24 hpdftbl_set_cell_label_cb()	17
14.3.5.25 hpdftbl_set_cellspan()	18
14.3.5.26 hpdftbl_set_col_content_style()	18
14.3.5.27 hpdftbl_set_colwidth_percent()	19
14.3.5.28 hpdftbl_set_content()	19
14.3.5.29 hpdftbl_set_content_cb()	20
14.3.5.30 hpdftbl_set_content_style()	
14.3.5.31 hpdftbl_set_content_style_cb()	21
14.3.5.32 hpdftbl_set_errhandler()	21
14.3.5.33 hpdftbl_set_header_halign()	
14.3.5.34 hpdftbl_set_header_style()	
14.3.5.35 hpdftbl_set_inner_border()	
14.3.5.36 hpdftbl_set_label_cb()	
14.3.5.37 hpdftbl_set_label_style()	
14.3.5.38 hpdftbl_set_labels()	
14.3.5.39 hpdftbl_set_outer_border()	
14.3.5.40 hpdftbl_set_row_content_style()	
14.3.5.41 hpdftbl_set_tag()	
14.3.5.42 hpdftbl_set_text_encoding()	
14.3.5.43 hpdftbl_set_title()	
14.3.5.44 hpdftbl_set_title_halign()	
14.3.5.45 hpdftbl_set_title_style()	
14.3.5.46 hpdftbl_stroke()	
14.3.5.47 hpdftbl_stroke_from_data()	
14.3.5.48 hpdftbl_stroke_grid()	
14.3.5.49 hpdftbl_table_widget_letter_buttons()	
14.3.5.50 hpdftbl_use_header()	
14.3.5.51 hpdftbl_use_labelgrid()	
14.3.5.52 hpdftbl_use_labels()	
14.3.5.53 hpdftbl_widget_hbar()	
14.3.5.54 hpdftbl_widget_segment_hbar()	
14.3.5.55 hpdftbl_widget_slide_button()	
14.3.5.56 hpdftbl_widget_strength_meter()	
14.4 hpdftbl.h	
14.5 / Users/ljp/Devel/hpdf_table/src/hpdftbl_errstr.c File Reference	
14.5.1 Detailed Description	
14.5.2 Function Documentation	
14.5.2.1 hpdftbl_hpdf_get_errstr()	41

169

14.6 /Users/ljp/Devel/hpdf_table/src/hpdftbl_grid.c File Reference			
	 	 	141
14.6.1 Detailed Description	 	 	142
14.6.2 Function Documentation	 	 	142
14.6.2.1 hpdftbl_stroke_grid()	 	 	142
14.7 /Users/ljp/Devel/hpdf_table/src/hpdftbl_widget.c File Reference	 	 	142
14.7.1 Detailed Description	 	 	143
14.7.2 Function Documentation	 	 	143
14.7.2.1 hpdftbl_table_widget_letter_buttons()	 	 	143
14.7.2.2 hpdftbl_widget_hbar()	 	 	144
14.7.2.3 hpdftbl_widget_segment_hbar()	 	 	145
14.7.2.4 hpdftbl_widget_slide_button()	 	 	145
14.7.2.5 hpdftbl_widget_strength_meter()	 	 	146
15 Example Documentation			147
15.1 tut_ex01.c	 	 	147
15.2 tut_ex02.c	 	 	148
15.3 tut_ex03.c	 	 	150
15.3 tut_ex03.c			
——————————————————————————————————————	 	 	151
15.4 tut_ex05.c	 	 	151 153
15.4 tut_ex05.c	 	 	151 153 154
15.4 tut_ex05.c	 	 	151 153 154 156
15.4 tut_ex05.c	 	 	151 153 154 156 158
15.4 tut_ex05.c  15.5 tut_ex06.c  15.6 tut_ex07.c  15.7 tut_ex08.c  15.8 tut_ex09.c	 	 	151 153 154 156 158 160
15.4 tut_ex05.c  15.5 tut_ex06.c  15.6 tut_ex07.c  15.7 tut_ex08.c  15.8 tut_ex09.c  15.9 tut_ex10.c	 	 	151 153 154 156 158 160 161
15.4 tut_ex05.c  15.5 tut_ex06.c  15.6 tut_ex07.c  15.7 tut_ex08.c  15.8 tut_ex09.c  15.9 tut_ex10.c  15.10 tut_ex11.c	 	 	151 153 154 156 158 160 161 163
15.4 tut_ex05.c  15.5 tut_ex06.c  15.6 tut_ex07.c  15.7 tut_ex08.c  15.8 tut_ex09.c  15.9 tut_ex10.c  15.10 tut_ex11.c  15.11 tut_ex12.c			151 153 154 156 158 160 161 163 164

Index

# Introduction to hpdftbl

#### 1.1 What is this?

The Haru PDF library is a great way to programmatically produce PDFs from programs. However, in many instances the best way to present data produced is as a grid (or table). To manually create and setup such tables int Haru PDF library is of course possible but only painstakingly so.

This C/C++ library libhpdftbl will facilitate the creation of tables with the Haru PDF library as well as handling the pesky issue of character conversion needed between UTF-8 and the internal standard used by PDF and Lib Haru. In addition to mere normal table the library also supports the creation of forms where each cell has a label similar to "formal" paper forms. This is a great way to present structured data from a DB.

This library provides a flexible abstraction for creating advanced tables with a model-view-controller like setup. This allows an easy way to separate the layout of the table from the actual data in the table.

#### 1.2 Features

- Supports both C/C++
- Suports both OSX/Linux builds and theire different dynamic library variants
- Fully supports UTF-8 with automatic conversion to PDF character encoding
- · Supports multple paradigms for creating and populating tables
  - Directly store value in table cell
  - Create a data structure (2D-Array) with all data to be set at once
  - Use callback populating functions with identifying tags for each table cell
- · Options to use labels in table cell to create forms
- · Support for predefined widgets in table cell to illustrate values
- · Complete control of background color, fonts, and frame colors
- Possible to use table themes that provides pre-defined look-and-feel for table
- · Both dynamic and static library provided
- Last but not least; extensive documentation and almost guaranteed to be bug free after beeing tested in production for over 7 years!

## 1.3 Some Examples

**Note:** All code examples can be found in the "`examples/`" directory and are thoroughly introduced over the following chapters.

## 1.3.1 Example 1 - Plain table with cell labels

Header 0	Header 1	Header 2	Header 3
Content 4	Content 5	Content 6	Content 7
Content 8	Content 9	Content 10	Content 11
Content 12	Content 13	Content 14	Content 15

### 1.3.2 Example 2 - Table with cell labels

Label 0:	Label 1:	Label 2:	Label 3:
Content 0	Content 1	Content 2	Content 3
Label 4:	Label 5:	Label 6:	Label 7:
Content 4	Content 5	Content 6	Content 7
Label 8:	Label 9:	Label 10:	Label 11:
Content 8	Content 9	Content 10	Content 11
Label 12:	Label 13:	Label 14:	Label 15:
Content 12	Content 13	Content 14	Content 15
Label 16:	Label 17:	Label 18:	Label 19:
Content 16	Content 17	Content 18	Content 19

1.3 Some Examples 3

## 1.3.3 Example 2 - Plain table with row/column spanning and table title

Example 3: Table cell spannings and full grid and header						
Cont	tent 0	Content 1				
Label 4:		Label 5:				
Content	4	Content	5			
Label 8:		Label 9:		Label 10:		
Content	8	Content	9	Content	10	
Label 12:		Label 13:		Label 14:		Label 15:
Content	12	Content	13	Content	14	Content 15
Label 16:		Label 17:				
Content	16	Content	17			
Label 20:		1				
Content	20					
Label 24:		Label 25:		Label 26:		Label 27:
Content	24	Content	25	Content	26	Content 27
Label 28:		Label 29:		Label 30:		
Content	28	Content	29	Content	30	
Label 32:		Label 33:		1		
Content	32	Content	33			

## 1.3.4 Example 3 - Table with labels and cell widgets

Example 5: Using widgets in cells						
Horizontal seg bar:	Label 1:		Label 2:		Label 3:	
40%	Content	1	Content	2	Content	3
Horizontal bar:	Label 5:		Label 6:		Label 7:	
60%	Content	5	Content	6	Content	7
Slider on:	Label 9:		Label 10:		Label 11:	
ON III	Content	9	Content	10	Content	11
Slider off:	Label 13:		Label 14:		Label 15:	
(III) OFF	Content	13	Content	14	Content	15
Strength meter:	Label 17:		Label 18:		Label 19:	
	Content	17	Content	18	Content	19
Boxed letters:	Label 21:		Label 22:		Label 23:	
ABCD	Content	21	Content	22	Content	23

Introduction to hp	απο	ı
--------------------	-----	---

# **Building the library**

#### 2.1 The short version

#### 2.1.1 Compiling the tar ball

If you downloaded the tar-ball then it should be trivial to build and install if you have the necessary pre-requisites. Just download the tar-ball and do the standard spell:

```
$ tar xzf libhpdftbl-1.0.0.tar.gz
$ cd libhpdf-1.0.0
$ ./configure && make
$ make install
```

If you miss any library the configure process will discover this and tell you what you need to install. This would otherwise compile and install the library in /usr/local subtree. It will build and install both a static and dynamic library.

Depending on your system this might also be available as a pre-built package for you to install directly via perhaps apton Linux or brew on OSX.

#### 2.1.2 Compiling after cloning the git repo

The repo does not include any generated files as the tar-ball does. This means that the following build tools needs to be setup in order to rebuild from a cloned repo.

- 1. A complete set of GNU compiler chain (or on OSX clang)
- 2. An installation of the autotools (autoconf, automake, libtool)
- 3. An installation of Doxygen (to generate documentation)

If these three pre-requisites are installed then the build environment is bootstrapped by running \$ ./scripts/bootstrap.sh

and then continue to compile

and (optionally) install the library \$ make install

6 Building the library

### 2.2 Pre-requisites

OSX Package manager: We recommend using brew as the package manager for OSX.

There are two external libraries required to rebuild libhpdftbl and more importantly use the library with an actual application and these are:

- 1. **libhpdf** The Haru PDF library. On OSX this is most easly installed by using the brew OSX package manager. The library is available as libharu as of this writing the latest version is libharu-2.3.0
- 2. iconv The character encoding conversion library. On OSX > 11.x this is included by default once you have xcode command line tools installed which is basically a pre-requisite required for all development on OSX. \*(On really old versions of OSX this was not the case.)\*

#### 2.3 Different versions of iconv on OSX

Unfortunately there are two main versions of libiconv readily available for OSX which are incompatible as one uses the prefix "`iconv\_\*`" and the other "`libiconv\_\*`" on its exported functions. Compiling libhpdftbl requires the first of these which is the prevelant version and the default on both OSX and Linux.

This is almost exclusivly an issue for those that actively develop on OSX and may have over time installed multiple versions of libraries and as such are aware of these challenges.

#### 2.3.1 OSX native libicony

After installing xcode command line tools on OSX you can assume that a library called /usr/lib/iconv.dylib is available. However, if you actually try to list this library in /usr/lib you will not find it! Still, if you link your code with -liconv it will work as expected. How come?

The reason is the way OSX handles different library versions for different OSX SDKs. Since xcode supports developing for different OSX versions the SDK would need to include a complete setup of all \*.dylib of the right version for each included version of the SDK. To reduce diskspace all dynamic librares are rolled-up in a dynamic link shared cache for each SDK version. The tool chain (e.g. gcc) have been augmented to be aware of this. Hence there is no need to have libraries in /usr/lib. Instead OSX from v11 and onwards uses the concept of  $stub\ libraries*.tbd$  (tbd stands for "text based description") which are much smaller text files with some meta information about the library used by the tool-chain.

For example for SDK 12.3 the stub for libiconv can be found at

 $/ \verb|Library/Developer/CommandLineTools/SDKs/MacOSX12.3.sdk/usr/lib/libiconv.tbd| \\$ 

and the corresponding include header at

/Library/Developer/CommandLineTools/SDKs/MacOSX12.3.sdk/usr/include/iconv.h

#### 2.3.2 OSX GNU port of libiconv

If you have happened to install libiconv via the MacPorts you are out of luck and need to change. MacPorts uses the GNU version which uses the prefix "`libiconv\_\*`" for its exported function and is not compatible since the table library assumes the naming convention of the standard OSX version (after v11)

#### 2.3.3 Troubleshooting OSX <tt>libiconv</tt>

1. Find out all installed versions of libiconv on your installation

```
$> find / -iregex '.*/libiconv.*' 2> /dev/null
```

The "`2> /dev/null`" makes sure you don't get a lot of noise "permission denied"

2. Find out the SDK path that is actively used

```
$> xcrun --show-sdk-path
```

3. Check you PATH variable

```
$> echo $PATH
```

## 2.4 Building the library from source

There are two levels of rebuilding the library

- 1. Using a build environment to rebuild the library
- 2. Rebuilding from a cloned repo and rebuild the build environment

#### 2.4.1 Rebuilding using a build environment

Rebuilding the library using a pre-configured build environment only requires gcc and make together with the standard C/C++ libraries to be installed.

The library source with suitable build-environments are distributed as two tar-balls, one setup for OSX and one setup for Linux in the Ubuntu flavor

- 1. libhpdf-src-x.y.z-osx.tar.gz
- 1. libhpdf-src-x.y.z-linux-ubuntu.tar.gz

These tar-balls include a build environment for each system as construced with the GNU autotools. This means that after downloading the appropriate tar-ball you can rebuild the library as so:

```
\ ./configure && make ... (output from the configuration and build omitted) ...
```

The git repo mimics the OSX tar ball as it is setup for a OSX based build environment. This means you do not need to install any special tools to rebuild the library on OSX. You only have to clone the repo and compile.

8 Building the library

#### 2.4.2 Rebuilding from the cloned repo

Rebuilding from the cloned repo requires the GNU autotools tool-chain to be installed. Since it is completely out of the scope decribing the intricities of the GNU autotools we will only show what to do assuming thie tool chain have been installed.

To simplify the potetially painful bootstrap of creating a full autotools environment a utility script that does this is provided in the form of "`scripts/bootstrap.sh`". After cloning the repo run (from the libhpdftbl directory) ./scripts/bootstrap.sh

This script will now run autoreconf, automake, glibtoolize as needed in order to create a full build environment. It will also run configure and if everything works as expected the last lines you will see (on OSX) will be

The final step you need to do is compile the library as so

\$> make -j4

The simplest way to verify that everything works is to execute one of the example programs (in the examples/directory) as so:

```
$> ./examples/example01
Stroking 5 examples.
Sending to file "/tmp/example01.pdf" ...
Done.
```

If you would like to install the library

\$> make install

This will install headers and library under "'/usr/local'".

#### 2.5 Some notes on Windows build

The source files are suitable augmented to also compile on MS Windows with selective defines. However, since I have no access to a Windows system to verify the workings this is left as an exercise to the reader.

### 2.6 Using C or C++ to build

The source files are also suitable augmented to compile on both a C and a C++ compiler. However, the default build environment is setup for a pure C library build. To add a configuration switch for this would be the sensible way to handle this. This is not done and again, is left as an exercise for the reader.

# **Getting started**

In this section we will introduce you to the basic usage of the hpdftbl library. We will start simple and work us all the way to complex tables and exaplin what is happening as we go along.

We will not assume any knowledge of the table library but we will assume that you are familiar with the plain Haru PDF library.

### 3.1 Creating a PDF page infrastructure

Before we start creating a table we need to setup a plain PDF page with the core HPDF library. The HPDF library has excellent documentation on how to do this and we will use the same simple setup for all our examples. We will create a document in A4 size that have one page. For this we use a few utility functions and our main() will always have the following structure:

```
main(int argc, char **argv) {
    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env)) {
        return EXIT_FAILURE;
    }
    setup_hpdf(&pdf_doc, &pdf_page, TRUE);
    create_table_<NAME_OF_EXAMPLE>(pdf_doc, pdf_page);
    stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
}
```

In the Appendix you can find the full code for the setup and troke function. They are very basic and follows the standard hpdf library methoddology. The  $setup\_hpdf()$  creates a new document and a A4 page and the  $stroke\_pdfdoc()$  strokes the document to the given output file.

In the following we will focus only on the  $create\_table\_<NAME\_OF\_EXAMPLE>$  () function which will use the two parameters  $pdf\_doc$  and  $pdf\_page$  to refer to the document and page to construct the table.

In order to make the examples robust and compatible with both Windows and Linux/OSX systems some conditional compile instructions are also used but we will not display them while discussing the basic usage to keep the focus on what matters.

The full source for all example are available in the <code>examples/</code> directory.

10 Getting started

#### 3.2 Your first table

```
tut_ex01.c
```

The first example shows the absolute most basic usage. We create a 2x2 table in steps as follows

First we construct a table handle for a 2x2 table

```
const size_t num_rows = 2;
const size_t num_cols = 2;
hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
```

Here we note that:

- · The size of the table has to be determined before the table handle is created
- Most other table function will refer to this handle and we will always use the varaiable name tbl for this handle
- We use size\_t instead of int since the table dimension is a size and as such can never be negative. In C it is always good practice to use size\_t for positive numeric entities.

Once we have the table handle we can start to add content in these cells. For now lets just put a string that indicates the cells position.

```
hpdftbl_set_cell(tbl, 0, 0, NULL, "Cell 0x0");
hpdftbl_set_cell(tbl, 0, 1, NULL, "Cell 0x1");
hpdftbl_set_cell(tbl, 1, 0, NULL, "Cell 1x0");
hpdftbl_set_cell(tbl, 1, 1, NULL, "Cell 1x1");
```

You can ignore the NULL argument for now (it will be explained shortly).

Here we note that:

• Cells are refered to starting from the top left cell that is cell (0x0)

Now its time to size and position the the table on the page. As a minimum you must specify the x and y position as well as the width of the table. The library is smart enough to automatically figure out the height (but it is also possible to force a larger height than strictly necessary)

The native coordiante system for PDF pages are given as the printing unit of DPI or *dots per inch*. By default the resolution of a PDF is 72 DPI.

To make it easier to directly set the size and position in centimeters a convenience function  $hpdftbl\_cm2dpi()$  can be used.

>For precision positioning it is more accurate to give the position and sizes in dots directly.

In this example we set the size and position in centimeters. We positionin the top left of the table *1cm* below and *1cm* to the right of the top left corner of the paper and make the table *5cm* wide as follows:

```
HPDF_REAL xpos = hpdftbl_cm2dpi(1);
HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
HPDF_REAL width = hpdftbl_cm2dpi(5);
HPDF_REAL height = 0; // Calculate height automatically
```

Now, there are several important observations to be made here:

• The origin of the paper coordinate system is bottom left which is (0,0)

- The anchor position by default is the top-left corner of the table (this can be adjusted by calling hpdftbl← \_set\_anchor\_top\_left (FALSE) function which will make the bottom left the anchor point instead)
- We use a predefined constant A4PAGE\_HEIGHT\_IN\_CM to position the table vertically 1 cm from the top
  of the paper
- We let the library calculate the minimum table height automatically (based on the font height used in the table)

Now the only thing remaining is to print or stroke the table to the page hpdftbl\_stroke(pdf\_doc, pdf\_page, tbl, xpos, ypos, width, height);

and we are done!

If we put it all together it will give us the following basic table creation code

```
create_table_ex01(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 2;
    const size_t num_cols = 2;

    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    hpdftbl_set_cell(tbl, 0, 0, NULL, "Cell 0x0");
    hpdftbl_set_cell(tbl, 0, 1, NULL, "Cell 0x1");
    hpdftbl_set_cell(tbl, 1, 0, NULL, "Cell 1x0");
    hpdftbl_set_cell(tbl, 1, 1, NULL, "Cell 1x1");
    hpdftbl_set_cell(tbl, 1, 1, NULL, "Cell 1x1");
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL vpos = hpdftbl_cm2dpi(1);
    HPDF_REAL width = hpdftbl_cm2dpi(5);
    HPDF_REAL height = 0; // Calculate height automatically hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}
```

The generated table is shown in **Figure 1**. ( tut\_ex01.c)

Figure 1: Your first table.

As we explained above the coordinate system is in postscript dots. For precision positioning it might be useful to visualize this grid on the page. By using the hpdftbl\_stroke\_grid() function such a grid can be displayed on a page to help with positioning. If we add the grid to the page and show the uppper left area of the paper with the grid we can view its positioning in the grid as shown in **Figure 2**.

```
Cell 0x0 Cell Cel
Cell 1x0 Cell 1x1
```

Figure 2: Your first table in the page coordinate system showing the upper left part of the paper.

Since this is an A4 page it will have a height of roughly 841 points or 29.7cm

## 3.3 Your second table - disconnecting program structure from data

One drawback of the program in the first example above is that if we want to have a different table size we need to actually change the code since we need one function call to store the data to be displayed in each cell. Wouldn't it be better if we could just suppply an array with the data we want to display?

```
The function to do just that is hpdftbl_set_content(hpdftbl_t tbl, char **content)
```

The content data is a 1-dimensional array of string pointers. Where ecah row is consecutive in the array. For example to create dummy data indicating what array position goes into what cell you could use the following setup:

```
typedef char **content_t;
void setup_dummy_data(content_t *content, size_t rows, size_t cols) {
    char buff[255];
    *content = calloc(rows*cols, sizeof(char*));
    size_t cnt = 0;
    for (size_t r = 0; r < rows; r++) {
        for (size_t c = 0; c < cols; c++) {
            snprintf(buff, sizeof(buff), "Content %zu", cnt);
            (*content)[cnt] = strdup(buff);
            cnt++;
        }
    }
}</pre>
```

12 Getting started

**Note:** We allocate each string dynamically in the dummy-data and since the program is just an illustration and terminates after the page has been created we never bother to free this memory. In a real life scenario this would of course be crucial!

We could then augment example 01 using this more efficient way to specify data as so:

```
void
create_table_ex02(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 2;
    const size_t num_cols = 2;
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    content_t content;
    setup_dummy_data(&content, num_rows, num_cols);
    hpdftbl_set_content(tbl, content);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL xpos = hpdftbl_cm2dpi(3);
    HPDF_REAL width = hpdftbl_cm2dpi(5);
    HPDF_REAL height = 0; // Calculate height automatically
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}

tut_ex02.c
```

Running the code above in our infrastructure will give

```
Content 0 Content 1
```

Figure 3: \*Specifying data in a table with an array of string pointers.( tut\_ex02.c)\*

In the above (small) example it might not have been a big safe but if you have a table with 20x10 rows \* cols then you will soon appreciate this way of specifying data.

There is even one more way of specifying data that in some situations are more efficient and allows a clear division between the table structure and look&feel and its data. This more efficient way is achieved by using cell callbacks either directly in individual cells or in one go by specifying the entire table as a data structure by using the hpdftbl\_stroke\_from\_data() function. This will be decribed later when we discuss how to use callback functions.

But now it is time to explain the NULL value in the first example when we specified the content with the  $\texttt{hpdftbl\_set\_cell}$  () function.

## 3.4 Adding a header row

While it is possible (as discussed in section ??) to manually adjust the font, size, style, background etc. on each cell individually there is a convinient shortcut to create a basic table with a header using the <a href="hpdftbl\_use\_header">hpdftbl\_use\_header</a>() function. By modifying the code above and add this line we get the following code and resulting table

```
void
create_table_exl1(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
    const size_t num_cols = 4;
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    hpdftbl_use_header(tbl, TRUE);
    content_t content;
    setup_dummy_data(&content, num_rows, num_cols);
    hpdftbl_set_content(tbl, content);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 5);
    HPDF_REAL height = 0; // Calculate height automatically
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}
```

The resulting table can be seen in **Figure 4**. We also modified the dummy data to have the work "Header" in the first row (for details see tut\_ex02\_1.c)

Figure 4: \*Adding automatic header formatted row ( tut\_ex02\_1.c)\*

#### 3.5 Using labels in the table cells

A variant of a table is to present data with a short label describing what kind of data is displayed. This is often used when a table is used to present a dataform. An example of this is shown in **Figure 4.** below.



Figure 4: \*Specifying labels for each cell. ( tut ex03.c)\*

Adding labels requires three things:

- 1. Enable the "label" feature with a call to hpdftbl\_use\_labels(tbl, TRUE);
- 2. Add the text that should be the label. Specifying these labels can either be done using the hpdftbl\_set\_cell() function as in hpdftbl\_set\_cell(tbl, 0, 0, "Label 1", "Cell 0x0"); hpdftbl\_set\_cell(tbl, 0, 1, "Label 2", "Cell 0x1"); hpdftbl\_set\_cell(tbl, 1, 0, "Label 3", "Cell 1x0"); hpdftbl\_set\_cell(tbl, 1, 1, "Label 4", "Cell 1x1");

or it can be done using the analog of specifying the labels in an array using the function hpdftbl\_set\_labels().

3. In addition there is one more key setting and that is whether the left cell border should be the whole cell or just the lable height as was shown in **Figure 4.** above. This option is specified with <a href="https://hpdftbl\_use\_labelgrid">hpdftbl\_use\_labelgrid</a>(). By defaullt the left border is from top to bottom. The differenceies between the two variants is shown in **Figure 5.** below.

```
MALE STATE OF THE STATE OF THE
```

Figure 5: The two variants of left cell border with labels.

Except for the simplest of tables both the table content and the labels should be specified in an array.

We therefore start by amending our dummy data creation function to also create the data for the labels. It will now look like this:

In the same way as before we call the functions to specify both the content and the labels

```
setup_dummy_data(&content, &labels, num_rows, num_cols);
hpdftbl_set_content(tbl, content);
hpdftbl_set_labels(tbl, labels);
```

and finally we also enable labels and the short variant of the left cell border

```
hpdftbl_use_labels(tbl, TRUE);
hpdftbl_use_labelgrid(tbl, TRUE);
```

the remaining code we can leave untouched. With this we get the result shown in **Figure 4.** with the full code for the table shown below.

```
void
create_table_ex04(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
   const size_t num_rows = 2;
   const size_t num_cols = 2;
```

14 Getting started

```
hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
content_t content, labels;
setup_dummy_data(&content, &labels, num_rows, num_cols);
hpdftbl_set_content(tbl, content);
hpdftbl_set_labels(tbl, labels);

hpdftbl_use_labels(tbl, TRUE);
hpdftbl_use_labelgrid(tbl, TRUE);
HPDF_REAL xpos = hpdftbl_cm2dpi(1);
HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
HPDF_REAL width = hpdftbl_cm2dpi(5);
HPDF_REAL height = 0; // Calculate height automatically
hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}

( tut_ex04.c)
```

### 3.6 Adding a table title

We have one last part of the table we haven't yet used and that is the table title. In the previous examples we created a table using hpdftbl\_create() but there is also hpdftbl\_create\_title(). A title can also be added to an existing table (or perhaps updated) using hpdftbl\_set\_title()

```
To create a table with a title
char *table_title = "tut_ex05: 2x2 table";
hpdftbl_t tbl = hpdftbl_create_title(num_rows, num_cols, table_title);
```

A table title occupies the top of the table in it's own row which isn't part of the counting if the normal columns.



Figure 6: \*Adding a title for the table. ( tut\_ex05.c)\*

It is possible to adjust the colors, font-properties, and aignments of the title with two additional functions hpdftbl\_set\_title\_style() and hpdftbl\_set\_title\_halign()

## 3.7 Adjusting fonts and colors

The one thing we have skipped over so far and just used the defaults is the look&feel of the table as far as colors and fonts go. It is possible to adjust these setting at several different granularities. It is possible to

- 1. Adjust the entire table in one go using hpdftbl\_set\_content\_style()
- 2. Adjust one entire column using hpdftbl\_set\_col\_content\_style()
- 1. Adjust one entire row in using hpdftbl\_set\_row\_content\_style()
- 1. Adjust individual cells using hpdftbl\_set\_content\_style()

It is also possible to adjust the color and thickness of the borders but we will not discuss this more here and instead refer the reader to the API documentation.

We should also mention that there is a concept of a look&feel theme for the table which can be used to adjust all the parameters at once. This is discussed in "Using themes".

# Adjusting the layout of the table

The table can be modified both by adjusting the width of columns as well as how many rows and columns a cell is spanning.

### 4.1 Cell and row spanning

A common way to modify a table is to have a cell spanning either multiple columns, multiple rows or both. This is done using the function

The specified (r,c) is the row and column of the upper left cell in merged cell that spans rowspan rows and colspans columns. This is also the row and col coordinates used to accessing the combined cell.

To illustrate this we will create a table with seven rows and five columns. We will merge three cells using these cell-spannings:

```
hpdftbl_set_cellspan(tbl, 0, 0, 1, 3);
hpdftbl_set_cellspan(tbl, 2, 2, 3, 3);
hpdftbl_set_cellspan(tbl, 3, 0, 4, 1);
```

For the data we will use the same setup as in  $tut_ex06.c$  This will then give the result shown in **Figure 8.** 



Figure 8: Having cells spanning multiple rows and columns.

## 4.2 Adjusting column width

By default or column widths are divided equally regardless of the content. The width can be adjusted by explicitly set the relative width of a column as a percentage of the total table width. This is done with the function

The width is set as a percentage of the total width and is specified as a floating point value in the range [0.0, 100.0]. An example of this is shown in **Figure 9.** below. An arbitrary number of columns can be given a width. For best result leave at least one column undefined and whatever remains of the table width will be assigned to that column. There is an error to try to specify a total column width > 100%.



Figure 9: Adjusting width of first columns.

Adi	iusting	the I	avout	of	the	table

## Content and label callbacks

In the "[Getting started](GettingStarted.md)" chapter we discussed the preferred way to specify data and labels in table using data arrays. This is a very good way to populate a table in the cases the data is fairly static.

For data that is more dynamic and determined at runtime it is of course possible to construct the data array but the table library have one better way to do this and that is to set up label and content callbacks.

### 5.1 Introducing content callback functions

Content callbacks are functions that are called by the table library for each cell and returns a string which is used as tne data to be displayed. The signature for a cell callback is defined by the type  $hpdftbl\_content\_callback\_t$  which is a pointer to a function defined as:

```
typedef char * (*hpdftbl_content_callback_t)(void *, size_t, size_t);
```

To understand this lets start with a callback function that follows this signature.

```
my_cell_cb(void *tag, size_t row, size_t col) { ... }
```

The parameters in the callback are

- 1. \*\*tag\*\*: Since a callback sometimes must know from what table or in what circumstances it is called it is possible to add a "tag" to ech table. This could be something as simple as pointer to a numeric identifier that uniquely identifies the table or perhaps a pointer to some function that retrives data for this particular table. The tag for a table is specified with the hpdftbl\_set\_tag () function. When the callback is made this table tag is provided as the first argument.
- 2. \*\*row\*\*: The cell row
- 3. \*\*col\*\*: The cell column

It is possible to specify a callback to adjust content, style, and labels. A callback function can be specified either for both the entire table as well as individual cells. The API to specify these callbacks are:

1. hpdftbl\_set\_content\_cb():
Specify a content callback for the entire table.

- hpdftbl\_set\_content\_style\_cb(): Specify a style callback for the entire table.
- 3. hpdftbl\_set\_label\_cb():
  Specify a label callback for the entire table.
- 4. hpdftbl\_set\_cell\_content\_cb():
  Specify callback for an individual cell. A cell callback will override a potential table callback.
- 5. hpdftbl\_set\_cell\_content\_style\_cb():
  Specify a style callback for an individual cell. A cell callback will override a potential table callback.
- 6. hpdftbl\_set\_canvas\_cb(): This is an advanced callback to allow for low level painting directly on the canvas that is the cell area. The arguments to the callback is different as it includes the bounding-box for th cell area. We will not further discuss this.

A note on the returned content string. When a content string is added in the table it is added as a copy of the string pointed to by the returned string pointer from the callback function. It is therefore perfectly possible to have a static allocated buffer in the callback function that is used to construct the content. When the table is destroyd using hpdftbl destroy() all used memory will be freed.

### 5.2 A content callback example

Let's now construct a simple example example where the content and the labels are specified with callbacks.

We will create callbacks that will add a date string to the top left cell and just som dummy content in the rest of the cells. We could do this in two ways.

- 1. Add a generic table callback for all cells and then in that callback check if the row and column is (0,0) i.e. top-left and in that case create a date.
- 2. Add a generic table callback for all cells and then add a specific cell callback with the date for the (0,0) cell.

To illustrate both methods we will use method 1 for the labels and method 2 for the content.

#### Let's first create the three callback functions we need

```
static char * cb_date(void *tag, size_t r, size_t c) {
    static char buf[64];
    time_t t = time(NULL);
    ctime_r(&t, buf);
    return buf;
}
static char * cb_content(void *tag, size_t r, size_t c) {
    static char buf[32];
    snprintf(buf, sizeof buf, "Content %02zu x %02zu", r, c);
    return buf;
}
static char * cb_labels(void *tag, size_t r, size_t c) {
    static char buf[32];
    if (0==r && 0==c) { // Top-left cell
        snprintf(buf, sizeof buf, "Date:");
    } else {
        snprintf(buf, sizeof buf, "Label %zux%zu:", r, c);
    }
    return buf;
```

We note that we ignore the tag argument. Since we only have one table there is no need to use a tag to different from which table a callback comes.

For the table structure we will re-use our previous example and create a 2x2 table and we get the following table creation code:

```
void
create_table_ex06(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 2;
    const size_t num_cols = 2;
    char *table_title = "tut_ex06: 2x2 table with calbacks";
    hpdftbl_t tbl = hpdftbl_create_title(num_rows, num_cols, table_title);
    hpdftbl_use_labels(tbl, TRUE);
    hpdftbl_use_labelgrid(tbl, TRUE);
    hpdftbl_set_label_cb(tbl, cb_labels);
    hpdftbl_set_content_cb(tbl, cb_content);
    hpdftbl_set_cell_content_cb(tbl, 0, 0, cb_date);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(12);
    HPDF_REAL height = 0; // Calculate height automatically
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}
( tut_ex05.c)
```

Running this example gives the result shown in Figure 7. below



Figure 7: Using callbacks to populate the table and labels.

Cont	tant	and	label	call	hac	ke
COIL	ισιιι	anu	Iavei	Lan	vac	NЭ

# **Error handling**

All library function will return an error code < 0 and also set a global variable to a specific error code that can later be read by an error handler. In order to translate the error to a human readable string the function  $hpdftbl\_get\_last\_errcode()$  can be used as the following error handling snippet examplified by a call to  $hpdftbl\_set\_colwidth\_percent()$ 

```
if( hpdftbl_set_colwidth_percent(tbl, 5, 110) ) {
    // This is an error
    char *err_str;
    int err_code, r, c;
    err_code=hpdftbl_get_last_errcode(&err_str, &r, &c);
    if( err_code ) {
        printf("*ERROR*: \"%s\" at cell (%d, %d)",err_str,r,c);
        exit(1);
    }
}
```

As can be seen from the snippet above it would yield quite longwinding error handling if one where to check every soingle library call. Instead there is the option of installing an error handler that would be called in the eent of an error.

```
The table error handle has the signature void hpdftbl_error_handler_t) (hpdftbl_t tbl, int r, int c, int err)
```

Where the arguments are

1. tbl The table in where the error happened. Note This might be NULL' since not all errors happen within the context of a table 2.r, CThe row and column if the error happens in a specified cell, otherwise these will be (-1,-1) 3.err` The internal error code. This si always a negative number.

The error handler is set with the hpdftbl\_set\_errhandler() method. An example of a very simple error handle is:

```
void
my_table_error_handler(hpdftbl_t t, int r, int c, int err) {
    if( r>-1 && c>-1 ) {
        fprintf(stderr, "*** Table Error: [%d] \"%s\" at cell (%d, %d)\n", err, hpdftbl_get_errstr(err), r, c);
    } else {
        fprintf(stderr, "*** Table Error: [%d] \"%s\" \n", err, hpdftbl_get_errstr(err));
    }
    exit(1);
}
```

In the above error handler we have made use of the utility function hpdftbl\_get\_errstr() that translates the internal error code to a human readable string.

In fact this exact error handler is available as a convinience in the librry under the name hpdftbl\_default\_\circ} table\_error\_handler so to use this trivial error handler just add the following line to your code hpdftbl\_set\_errhandler(hpdftbl\_default\_table\_error\_handler);

More advanced error handler must be written for thr particular application they are to be used in.

22 Error handling

**Note:** A common way to extend the error handling is to log the errors to syslog. When the library is used on OSX from 11.0 and onwards it should be rememberd that OSX is broken by design as far as syslog logging is concerned. Apple in its wisdom introduced "Unified logging" which breaks the syslog() function and no logging is ever produced in the filesystem directly (i.e. to /var/log/system.log). Instead the only way to view the logs is by using the utility log. So in order to view the log from a particular application the following command has to be given

'log stream --info --debug --predicate 'sender == "APPLICATION\_NAME"' -style syslog`

### 6.1 Translating HPDF error codes

The standard error handler for the plain HPDF library is specified when a new document is created, for example as'

```
pdf_doc = HPDF_New(error_handler, NULL);
HPDF_SetCompressionMode(pdf_doc, HPDF_COMP_ALL);
```

The error handler signature is defined by Haru PDF library as

```
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no, void *user_data);
```

It is then up to the application code to decide how to handle the error. To simplify the handling of core HPDF error the library also offer a convinience function to translate the Haru library error code into a human readable string. This function is

```
const char *
hpdftbl_hpdf_get_errstr(const HPDF_STATUS err_code)
```

and is used in the error handler in all the examples.

## 6.2 Example of setting up error handler

The following table creation code have a deliberate error in that it tries to assign a total column width of more than 100% which of course isn't possible.

```
create_table_ex10(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
    const size_t num_cols = 4;
    hpdftbl_set_errhandler(hpdftbl_default_table_error_handler);
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    hpdftbl_set_colwidth_percent(tbl, 0, 40);
    hpdftbl_set_colwidth_percent(tbl, 1, 70);
    content_t content;
    setup_dummy_data(&content, num_rows, num_cols);
    hpdftbl_set_content(tbl, content);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL xpos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 4);
    HPDF_REAL height = 0; // Calculate height automatically
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}
```

This is available in the example directory as tut\_ex10.c. When this code is executed the following will be printed to standard out and the process will be stopped.

```
*** Table Error: [-12] "Total column width exceeds 100%"
```

# Style and font setting

The format of each cell can be adjusted with respect to:

- 1. Font-family and style (size, bold, italic etc.)
- 2. Font- and background-color
- 3. Border thickness and color

In this section we will focus on how to adjust the font and background color. The styld can be adjusted both forthe entire table at once and alse for individual cells. The individual cell style will always override the table cell style.

#### The primary API to adjust the table style are:

```
// Set background color for entire table
int hpdftbl_set_background(hpdftbl_t t,
                         HPDF RGBColor background);
// Set label style for the entire table
int hpdftbl_set_label_style(hpdftbl_t t,
                          char *font, HPDF_REAL fsize,
                         HPDF_RGBColor color, HPDF_RGBColor background);
// Set content style for entire table
HPDF_RGBColor color, HPDF_RGBColor background);
// Set conten style for specified cell
int hpdftbl_set_cell_content_style(hpdftbl_t t,
                                 size_t r, size_t c
                                 char *font, HPDF_REAL fsize,
                                 HPDF_RGBColor color, HPDF_RGBColor background);
// Set content style for specified row in table
int hpdftbl_set_row_content_style(hpdftbl_t t,
                               size_t r,
                                char *font, HPDF_REAL fsize,
                                HPDF_RGBColor color, HPDF_RGBColor background);
// Set content style for specified column in table
int hpdftbl_set_col_content_style(hpdftbl_t t,
                                char *font, HPDF_REAL fsize,
                                HPDF_RGBColor color, HPDF_RGBColor background);
```

## 7.1 Specifying fonts and colors

Fonts are specified as a string with the type font family name as recognized by the core Haru PDF library, e.g. "Times-Roman", "Times-Italic", "Times-Bold" etc. As a convenience not to have to remember the exact font name strings the following three font family are defined as HPDF\_FF\_\* where the last part of the name is specified as the following table shows

24 Style and font setting

Font family	Italic	Bold	BoldItalic
TIMES	TIMES_ITALIC	TIMES_BOLD	TIMES_BOLDITALIC
HELVETICA	HELVETICA_ITALIC	HELVETICA_BOLD	HELVETICA_BOLDITALIC
COURIER	COURIER_ITALIC	COURIER_BOLD	COURIER_BOLDITALIC

Table 1: Predefined font family and variants

So to use the "Helvetic" font family the constant "`HPDF\_FF\_HELVETICA`" is used and so on.

Colors are specified in the standard Haru way, i.e as an instance of the structure "`HPDF\_RGBColor`". As another convenience the following colors are predefined

```
(HPDF_RGBColor) { 0.6f, 0.0f, 0.0f
#define COLOR_RED
                              (HPDF_RGBColor) {
                                                1.0f, 0.0f, 0.0f
#define COLOR_LIGHT_GREEN
                              (HPDF_RGBColor) { 0.9f, 1.0f, 0.9f
                              (HPDF_RGBColor) { 0.4f, 0.9f, 0.4f
(HPDF_RGBColor) { 0.2f, 0.2f, 0.2f
#define COLOR_GREEN
#define COLOR_DARK_GRAY
#define COLOR_LIGHT_GRAY
                              (HPDF_RGBColor) { 0.9f, 0.9f, 0.9f
#define COLOR_GRAY
                              (HPDF_RGBColor) { 0.5f, 0.5f, 0.5f
#define COLOR_SILVER
                              (HPDF_RGBColor) { 0.75f, 0.75f, 0.75f
#define COLOR_LIGHT_BLUE
                              (HPDF_RGBColor) { 1.0f, 1.0f, 0.9f
#define COLOR_BLUE
                              (HPDF_RGBColor) { 0.0f, 0.0f, 1.0f
#define COLOR WHITE
                              (HPDF RGBColor) {
                                                1.0f, 1.0f,
                              (HPDF_RGBColor) { 0.0f, 0.0f, 0.0f
#define COLOR_BLACK
```

So for example to set the overall default font to 12pt Times Roman with black text on white bottom the following call must be made

```
...
hpdftbl_set_content_style(tbl, HPDF_FF_TIMES, 12, COLOR_BLACK, COLOR_WHITE);
...
```

Since RGB for colors are specified as a flotaing point number in range [0.0, 1.0] and most color table give colors as a integer triple there is exists a macro to make this conversion easier

```
which will allow the easier specification of color such as HPDF_RGBColor color_saddle_brown = HPDF_COLOR_FROMRGB(139,69,19);
```

### 7.2 Using style callbacks

In much the same way as callbacks can be used for specifying content and labels so can a callback be used to specify the style of a cell or the entire table.

```
A style callback has the following signature
```

```
_Bool hpdftbl_content_style_callback_t(void *tag, size_t r, size_t c, char *content, hpdf_text_style_t *style);
```

In order for the settings to be applied the callback has to return a boolean TRUE value.

If the callback returns  ${\tt FALSE}$  the settings will  $\boldsymbol{not}$  be applied.

The parameters are used as follows:

- The tag parameter has the same meaning as for content and label callbacks; an optional unique identifier for the table.\*\* The tag parameter should always be checked for possible NULL value since it is not required for a table to have a tag.
- The  ${\tt r}$  and  ${\tt c}$  arguments are the row and column of the cell the callback is made for
- The content is the cell content string. The rationale for including this in the style callback is to allow for highlightning in the table of specific data. It could for example be something as simple as wanting to mark all values above a certain threshold with another background color in the table to draw attention.

 Finally the actual style is encompassed by the hpdf\_text\_style\_t and is defined as the following structure

```
typedef struct text_style {
    char *font;
    HPDF_REAL fsize;
    HPDF_RGBColor color;
    HPDF_RGBColor background;
    hpdftbl_text_align_t halign;
} hpdf_text_style_t;
```

The style callbacks can exactly as the content callback be specified for either the entire table or for a specific cell. A cell callback will always override a table callback. The two functions to setup style callbacks are

**Note:** Due to som technicalities **the style callbacks** are **called twice** per cell. The first call is necessary to setup the background canvas and at that stage the content is not necessarily known since it could be later specified with a content callback. The first time the callback is made the content parameter is always guaranteed to be NULL

## 7.2.1 Style callback example

An example of a callback function to set a background color for a header row/column for a table could for example be done as follows

```
_Bool
cb_style(void *taq, size_t r, size_t c, char *content, hpdf_text_style_t *style) {
    // Format the header row/column with a grey background and Helvetica font while the rest of the
    // table uses "Times Roman"
    if( 0==r || 0==c ) { // Headers
        style->font = HPDF_FF_HELVETICA_BOLD;
        style->fsize = 12;
        style->color = COLOR BLACK:
        style->background = COLOR_LIGHT_GRAY;
        if (c > 0)
            style->halign = CENTER;
        else
    style->halign = LEFT;
} else { // Content
        style->font = HPDF_FF_TIMES;
        style->fsize = 11;
        style->color = COLOR_BLACK;
        style->background = COLOR_WHITE;
        style->halign = CENTER;
    return TRUE;
}
```

and the table setup code can then be written as

```
void
create_table_ex09(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
    const size_t num_cols = 4;
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    hpdftbl_set_content_cb(tbl, cb_content);
    hpdftbl_set_content_style_cb(tbl, cb_style);
    hpdftbl_set_colwidth_percent(tbl, 0, 40);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 4);
    HPDF_REAL height = 0; // Calculate height automatically
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
}
```

The resulting table is shown in Figure 10. below.

```
Figure 10: Using a style callback to highlight header rows & columns. tut_ex09.c
```

26 Style and font setting

## 7.3 Using style themes

if you have multiple table in a document it is possible to create a *table theme* which consiste of some core styling of a table that can be reused. The data saved in a theme is defined by the structure hpdftbl\_theme whithe the following defintion and members

```
typedef struct hpdftbl_theme {
   hpdf_text_style_t *content_style;
   hpdf_text_style_t *label_style;
   hpdf_text_style_t *header_style;
   hpdf_text_style_t *title_style;
   hpdf_border_style_t *inner_border;
   hpdf_border_style_t *outer_border;
   _Bool use_labels;
   _Bool use_label;
   _Bool use_header_row;
} hpdftbl_theme_t;
```

This allow the setting of all main font/style setting in one go. This structure can be set up manually and then applied to a table. However, the recommended way is to first use the "theme getter" function to get the default theme and then modify this default theme as needed. The functions to work with a theme are:

```
// Apply the given theme to a table
int
hpdftbl_apply_theme(hpdftbl_t t, hpdftbl_theme_t *theme);
// Get the default theme into a new allocated structure
hpdftbl_theme_t *
hpdftbl_get_default_theme(void);
// Destroy the memory used by a theme
int
hpdftbl_destroy_theme(hpdftbl_theme_t *theme);
```

>Note: It is the responsibility of the user of the library to destroy the theme structure by ensuring that hpdftbl\_destroy\_theme() is called when a theme goes out of scope.

The default font styles for the default theme are shown in table 1.

Style	Font	Size	Color	Background	Alignment
content	HPDF_FF_COURIER	10	Black	White	Left
label	HPDF_FF_TIMES_ITALIC	9	Dark gray	White	Left
header	HPDF_FF_HELVETICA_BOLD	10	Black	Light gray	Center
title	HPDF_FF_HELVETICA_BOLD	11	Black	Light gray	Left

Table 1: Default font styles.

Theme parameter	Default value
use_labels	FALSE
use_label_grid_style	FALSE
use_header_row	FALSE

Table 2: Default table structure parameters.

Border	Color	Width (pt)
inner_border	Grey	0.7
outer_border	Dark Grey	1.0

Table 3: Default border parameters.

7.3 Using style themes 27

**Note:** There is currently no support for serializing a theme to/from a file.

Style	and	font	setting
-------	-----	------	---------

# **Chapter 8**

# **Tables layout from data**

So far we have constructed the layout of table by issuing API calls per table to setup, for example, the column widths and what cells should merge with what other cells and so on. Previously we saw that data to be put in the table could be specified by either directly issuing API calls per cell, using a 2D array that we populate with data and then finally use callbacks to generate the data in the cells.

The final and most powerful way of constructing a table is to define the table structure as data. This *structural data* together with a style theme can completely define a table.

This will allow the dynamic construction of tables with only one API call insted of the multiple call required to construct a table the usual way. It can initially seem more complex but for advanced table this is indeed a much simpler and easy to maintain. In fact, this will allow a table to bed defined entirely in a database and makes it possible to adjust tha table as the data changes without ever updating the code (or recompile).

# 8.1 Defining a table in data

There are two data structure that are used when defining a table. First there is a data structure for the overall table specifics and then in that structure a structure to specify the layout of each cell. In addition a theme needs to be defined as was discussed in secion ??. It is possible to omit the theme by specifying NULL in which case the default theme will be used.

To stroke a table from data the following API call is used

```
int
hpdftbl_stroke_from_data(HPDF_Doc pdf_doc, HPDF_Page pdf_page, hpdftbl_spec_t tbl_spec, hpdftbl_theme_t
    *theme);
```

In order to populate the table with suitable data callback functions are used (as decribed in section ??)

The overall table is first defined as an instance of

```
typedef struct hpdftbl_spec {
    char *title:
    Bool use header;
    _Bool use_labels;
    _Bool use_labelgrid;
    size_t rows;
    size_t cols;
    HPDF_REAL xpos;
HPDF_REAL ypos;
    HPDF_REAL width;
    HPDF_REAL height;
    hpdftbl_content_callback_t content_cb;
    hpdftbl_content_callback_t label_cb;
    hpdftbl_content_style_callback_t style_cb;
    hpdftbl_callback_t post_cb;
    hpdftbl_cell_spec_t *cell_spec;
} hpdftbl_spec_t;
```

Then each cell (referenced above in the cell\_spec field) is defined as an instance of

```
typedef struct hpdftbl_cell_spec {
    size_t row;
    size_t col;
    unsigned rowspan;
    unsigned colspan;
    char *label;
    hpdftbl_content_callback_t content_cb;
    hpdftbl_content_callback_t label_cb;
    hpdftbl_content_style_callback_t style_cb;
    hpdftbl_canvas_callback_t canvas_cb;
} hpdftbl_cell_spec_t;
```

## 8.2 A first example of defining table as data

To understand how this is done lets start to define a basic 3x3 table with header row (so 4x3 in total) as data. First we create an instance of the table data

```
hpdftbl spec t tbl spec = {
         // Title and header flag
         .title=NULL, .use_header=TRUE,
        // Label and labelgrid flags
         .use_labels=FALSE, .use_labelgrid=FALSE,
         // Row and columns
         .rows=4, .cols=3,
         // xpos and ypos
         .xpos=hpdftbl_cm2dpi(1), .ypos=hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM-2),
           width and height
         .width=hpdftbl_cm2dpi(15), .height=0,
        // Content and label callback
        .content_cb=cb_content, .label_cb=cb_label,
// Style and table post creation callback
         .style_cb=NULL, .post_cb=NULL,
        // Pointer to optional cell specifications
         .cell_spec=NULL
};
```

>Note: In the table definition we use the C99 feature of specifying the field name when defining data in a structure.

Then the actual API call is trivial to what we seen before and consists of only one line of code

```
void
create_table_ex13_1(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
   hpdftbl_stroke_from_data(pdf_doc, pdf_page, &tbl_spec, NULL);
}
```

The result is as expected and shown in Figure 13 but with much less code!

Figure 13: Defining a table with a data structure tut\_ex13\_1.c

## 8.3 A second example of defining a table as data

In the previous example we kept it simple didn't specify any format or content fór a table cell. Let us therefore create a slightly more complex example where we create a form which easily could be used to display data records from a DR

The nice thing about separating layout and table structure from the data population in the callbacks is that this can almost be seen as a poor mans model-view-controller where the table structure is completely separate from the

A good way to start designing a table is to make a sketch on how it should look. Our goal is to crete the table structure as shown in the empty table in **Figure 14** below



Figure 14: Sketch of table to be designed

To get this layout we use a basic table with:

- 1. Five rows and four columns
- 2. No header and no title
- 3. We use labels and label grids

To make it easier to see how to construct the table we can overlay the sketch with a grid shown in blue in **Figure** 15. As can be seen this is a basic 5x4 table where a number or cells span multiple columns.



Figure 15: Sketch of table to be designed with 5x4 table overlayed

To start we setup the table specification as in the previous example with necessary changes. We will also need to specify cell specifications this time and we assume those are available in an array of cell structures called cellcospecs.

Before we specify the table structure we have one design decision to make. For the callbacks we can either use the table callback for all cells and check row and column to get the appropriate data or we can add individual callbacks for each cell. The first case has the advantage to only need one callback function (but lot of tests) and the second that each callback will be small and focused to get the data for that individual cell but we will need potentially one callback for each cell unless there are commonalities between the cells so one callback can serve multiple cells. Remember that we still get the row and column as arguments in the callback so we weill always know exactly for which cell the callback was made.

To keep the size of this example we will use the table callback method for content and specify the label directly in the cell specification. With this decision made we get the following definition cell specifications

```
hpdftbl_cell_spec_t cell_specs[] =
         {.row=0, .col=0, .rowspan=1, .colspan=3,
.label="Name:",
          .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL),
         {.row=0, .col=3, .rowspan=1, .colspan=1,
          .label="Date:
          .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
                    .col=0, .rowspan=1, .colspan=4,
          .label="Address:",
           .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=2, .col=0, .rowspan=1, .colspan=3,
   .label="City:",
           .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=2, .col=3, .rowspan=1, .colspan=1,
.label="Zip:",
          .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
          .row=3, .col=0, .rowspan=1, .colspan=4,
.label="E-mail:",
         \{.row=3,
          .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=4, .col=0, .rowspan=1, .colspan=2,
.label="Workphone:",
           .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=4, .col=2, .rowspan=1, .colspan=2,
  .label="Mobile:",
          .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL), HPDFTBL_END_CELLSPECS // Sentinel to mark the end of
```

As can be seen we need to have a end of cell specification sentinel since we could decide to provide details for one or more cells and there is no way for the library to know how many fields to read otherwise. There is even a convenience constant in the library PDFTBL END CELLSPECS that can be used as the last record.

The overall table specification is pretty much as before but with the added cell specifications.

```
hpdftbl_spec_t tbl_spec = {
    // Title and header flag
    .title=NULL, .use_header=FALSE,
    // Label and labelgrid flags
    .use_labels=TRUE, .use_labelgrid=TRUE,
    // Row and columns
    .rows=5, .cols=4,
    // xpos and ypos
    .xpos=hpdftbl_cm2dpi(1), .ypos=hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM-2),
    // width and height
    .width=hpdftbl_cm2dpi(15), .height=0,
    // Content and label callback
    .content_cb=cb_content, .label_cb=cb_label,
```

```
// Style and table post creation callback
.style_cb=NULL, .post_cb=NULL,
// Pointer to optional cell specifications
.cell_spec=cell_specs
};
```

When this is run (see tut\_ex13\_2.c) it generates the following image, Figure 13.2



Figure 16: Specifying a table as data with cell specifications.

What remains is to write the proper table content callback that will populate the table. In a real life scenario his data will most likely come from a database but adding that in our example would bring to far. Instead we will just use some fake static dummmy data to illustrate the principle.

Since we have one callback for all cells we need to test from which cell the call come from. Here is a very important point to make. The row and column number will be the row and cell columns in the original table before any column or row spans was applied. In this example it means that for example the "Date" field (upper right) will have row=0 and col=3 and not (0,1)!!.

With this information we can write the following (dummy) table callback

```
static char >
cb_content(void *tag, size_t r, size_t c) {
    static char *cell_content[] =
            {"Mark Ericsen",
             "12 Sep 2021",
             "123 Downer Mews",
             "London",
             "NW2 HB3",
             "mark.p.ericsen@myfinemail.com",
             "+44734 354 184 56",
             "+44771 938 137 11"};
    if( 0==r && 0==c) return cell_content[0];
    else if (0==r && 3==c) return cell_content[1];
    else if (1==r && 0==c) return cell_content[2];
    else if (2==r && 0==c) return cell_content[3];
    else if (2==r && 3==c) return cell_content[4];
    else if (3==r && 0==c) return cell_content[5];
    else if (4==r && 0==c) return cell_content[6];
    else if (4==r && 2==c) return cell_content[7];
    else return NULL;
```

and we get the (expected) result as shown in Figure 17 below.



Figure 17: Specifying a table as data with cell specifications and "dummy" data.

The alternative of specifying individual callback for each cell would then require that each cell have a callback provided or perhaps even a mix with both a general table callback and selected cell callbacks.

The priority is such that a cell callback will always override a table callback. In the above example the callback for the name field could as an example be

```
static char *
cb_content_name (void *tag, size_t r, size_t c) {
    static char *cell_content = "Mark Ericsen";
    return cell_content;
}
```

**Chapter 9** 

**Using Widgets** 

**Using Widgets** 34

# **Chapter 10**

# **HPDFTBL API Overview**

#### 10.1 Table creation related functions

These calls relate to the creation, destruction and stroking of the table on the PDF page.

- hpdftbl\_create() Create a handle for a new table.
- hpdftbl\_create\_title() Create a handle for a new with a title.
- hpdftbl\_destroy() Destroy (return) memory used by a table.
- hpdftbl\_stroke() Stroke a table on the specified PDF page.
- hpdftbl stroke from data() Construct and stroke a table defined as a data structure.
- hpdftbl\_get\_last\_auto\_height() Get the height of the last table stroked.
- hpdftbl\_set\_anchor\_top\_left() Switch the anchor point of a table betwen top left and bottom left corner.
- hpdftbl\_get\_anchor\_top\_left() Get the current achor point of table.

## 10.2 Table error handling

- hpdftbl\_set\_errhandler() Set and error handler callback.
- hpdftbl\_get\_errstr() Translate an error code into a human readable string.
- hpdftbl\_get\_last\_errcode() Get the error code from last error raised
- hpdftbl\_default\_table\_error\_handler() A default error handler callback that print error to stdout and quits the process.

## 10.3 Theme handling methods

Themes is a technique to easier specify the look and feel to be re-used for multiple tables.

- hpdftbl\_apply\_theme() Use the specified theme for look & feel of tabl.e
- hpdftbl\_get\_default\_theme() Get the default theme. A good way to start and then modify.
- hpdftbl\_destroy\_theme() Free all memory structures used by a theme.

36 HPDFTBL API Overview

## 10.4 Table layout adjusting functions

Adjusting the structure of the table (apart from number of rows and columns)

- · hpdftbl\_set\_colwidth\_percent() Set the column width as a percentage of the entire table width.
- hpdftbl set cellspan() \*Define a cell to span multiple rows and columns."
- hpdftbl\_clear\_spanning() Remove all previous set cell spanning.

## 10.5 Table style modifying functions

These function are all about look an feel of the table.

- hpdftbl use labels() Use labels in each cell.
- · hpdftbl\_use\_labelgrid() Use shorter left gridlines that only goes down and cover labels
- hpdftbl\_set\_background() Set cell background color.
- hpdftbl\_set\_outer\_border() Set style of the table outer border.
- hpdftbl\_set\_inner\_border() Set the style of table inner borders.
- hpdftbl\_set\_header\_style() Set the style for the table header row.
- hpdftbl\_set\_header\_halign() Set the horizontal alignment of the header row.
- hpdftbl\_set\_title\_halign() Set horizontal alignment for title.
- hpdftbl\_use\_header() Make the top row a header.
- hpdftbl\_set\_label\_style() Set style for cell labels.
- hpdftbl\_set\_row\_content\_style() Set the content style for an entire row.
- hpdftbl\_set\_col\_content\_style() Set the content style for an entire column.
- hpdftbl\_set\_content\_style() Set the content style for the entire table.
- hpdftbl\_set\_cell\_content\_style() Set the stle for specified cell. This overrides andy style on the table level.
- hpdftbl\_set\_title\_style Set the style for the table title.

## 10.6 Content handling

Content in a table can be specified in three ways

- 1. Manually for each cell by calling the hpdftbl set cell() function
- 2. In one go by creating a 1D data array for all cell
- 3. Creating a callback which returns the wanted value
- hpdftbl\_set\_cell() Set content text in specified cell.
- hpdftbl\_set\_tag() Set the table tag. The tag is a void \* an can be anything. The tag is the first parameter
  of all callbacks.
- hpdftbl\_set\_title() Set title text of table.
- hpdftbl\_set\_labels() Set label texts for the table from 1D-data array.
- hpdftbl\_set\_content() Set the content text for the entire table from a 1D-data array.

10.7 Callback handling 37

## 10.7 Callback handling

Callbacks can be specified on both table but also on cell level. The simple rule is that if a cell has a callback that is used, otherwise the table callback is used.

- hpdftbl set content cb() Set table content callback.
- hpdftbl\_set\_cell\_content\_cb() Set cell content callback.
- hpdftbl\_set\_cell\_content\_style\_cb() Set the cell style callback.
- hpdftbl\_set\_content\_style\_cb() Set the table style callback.
- hpdftbl\_set\_label\_cb() Set table label callback.
- hpdftbl\_set\_cell\_label\_cb() Set the cell label callback.
- hpdftbl\_set\_canvas\_cb() Set table canvas callback.
- hpdftbl\_set\_cell\_canvas\_cb() Set the cell canvas callback.

## 10.8 Text encoding

- hpdftbl\_set\_text\_encoding() Specify text encodation to use.
- hpdftbl\_encoding\_text\_out() Stroke a text with current encoding.

## 10.9 Misc utility function

- HPDF\_RoundedCornerRectangle() Draw a rectanle with rounded corners.
- hpdftbl\_stroke\_grid() \*Stroke a grid on the PDF page (entire page). This is useful to position the table on a page. The grid is measured in points i.e. postscript natural units.

38 **HPDFTBL API Overview** 

# **Chapter 11**

# **Data Structure Index**

# 11.1 Data Structures

Here are the data structures with brief descriptions:

border_style	
Specification for table borders	13
hpdftbl	
Core table handle	4
hpdftbl_cell	
Specification of individual cells in the table	19
hpdftbl_cell_spec	
Used in data driven table creation	51
hpdftbl_errcode_entry	
An entry in the error string table	64
hpdftbl_spec	
Used in data driven table creation	64
hpdftbl_theme	
Define a set of styles into a table theme	8
line_dash_style	
Definition of a dashed line style	60
text_style	
Specification of a text style	31

40 **Data Structure Index** 

# **Chapter 12**

# File Index

# 12.1 File List

Here is a list of all documented files with brief descriptions:

/Users/ljp/Devel/hpdf_table/src/config.h	33
/Users/ljp/Devel/hpdf_table/src/hpdftbl.c	
Main source module for hpdftbl	34
/Users/ljp/Devel/hpdf_table/src/hpdftbl.h	
Necessary header file for HPDF table usage	94
/Users/ljp/Devel/hpdf_table/src/hpdftbl_errstr.c	
Utility module to translate HPDF error codes to human readable strings	40
/Users/ljp/Devel/hpdf_table/src/hpdftbl_grid.c	
Create a grid on a document for positioning	41
/Users/ljp/Devel/hpdf_table/src/hpdftbl_widget.c	
Support for drawing widgets	42

42 File Index

# **Chapter 13**

# **Data Structure Documentation**

# 13.1 border\_style Struct Reference

Specification for table borders.

```
#include <hpdftbl.h>
```

#### **Data Fields**

- HPDF\_REAL width
- HPDF\_RGBColor color
- hpdftbl\_line\_style\_t line\_style

## 13.1.1 Detailed Description

Specification for table borders.

Contains line properties used when stroking a border line

#### 13.1.2 Field Documentation

#### 13.1.2.1 color

HPDF\_RGBColor color

Color of line

## 13.1.2.2 line\_style

```
hpdftbl_line_style_t line_style
```

Line style (currently not used, preparation for future extensions)

#### 13.1.2.3 width

HPDF\_REAL width

Line width of border

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

## 13.2 hpdftbl Struct Reference

Core table handle.

#include <hpdftbl.h>

#### **Data Fields**

- HPDF\_Doc pdf\_doc
- HPDF\_Page pdf\_page
- size t cols
- size\_t rows
- HPDF\_REAL posx
- HPDF\_REAL posy
- HPDF\_REAL height
- HPDF\_REAL width
- void \* tag
- char \* title\_txt
- hpdf\_text\_style\_t title\_style
- hpdf\_text\_style\_t header\_style
- \_Bool use\_header\_row
- hpdf\_text\_style\_t label\_style
- \_Bool use\_cell\_labels
- \_Bool use\_label\_grid\_style
- hpdftbl\_content\_callback\_t label\_cb
- · hpdf text style t content style
- hpdftbl\_content\_callback\_t content\_cb
- hpdftbl\_content\_style\_callback\_t content\_style\_cb
- hpdftbl\_canvas\_callback\_t canvas\_cb
- hpdftbl\_cell\_t \* cells
- hpdf\_border\_style\_t outer\_border
- · hpdf border style tinner border
- float \* col\_width\_percent

## 13.2.1 Detailed Description

Core table handle.

This is the main structure that contains all information for the table. The basic structure is an array of cells.

See also

```
hpdftbl_cell_t
```

#### **Examples**

 $tut_ex01.c$ ,  $tut_ex02.c$ ,  $tut_ex03.c$ ,  $tut_ex05.c$ ,  $tut_ex06.c$ ,  $tut_ex07.c$ ,  $tut_ex08.c$ ,  $tut_ex09.c$ ,  $tut_ex10.c$ ,  $tut_ex11.c$ , and  $tut_ex12.c$ .

#### 13.2.2 Field Documentation

#### 13.2.2.1 canvas\_cb

```
hpdftbl_canvas_callback_t canvas_cb
```

Table canvas callback. Will be called for each cell unless the cell has its own canvas callback

#### 13.2.2.2 cells

```
hpdftbl_cell_t* cells
```

Reference to all an array of cells in the table

#### 13.2.2.3 col\_width\_percent

```
float* col_width_percent
```

User specified column width as fraction of the table width. Defaults to equ-width

#### 13.2.2.4 cols

size\_t cols

Number of columns in table

Referenced by hpdftbl\_set\_row\_content\_style().

#### 13.2.2.5 content\_cb

```
{\tt hpdftbl\_content\_callback\_t\ content\_cb}
```

Table content callback. Will be called for each cell unless the cell has its own content callback

#### 13.2.2.6 content\_style

```
hpdf_text_style_t content_style
```

Content style

#### 13.2.2.7 content\_style\_cb

```
hpdftbl_content_style_callback_t content_style_cb
```

Style for content callback. Will be called for each cell unless the cell has its own content style callback

#### 13.2.2.8 header\_style

```
hpdf_text_style_t header_style
```

Header style

#### 13.2.2.9 height

```
HPDF_REAL height
```

Table height. If specified as 0 then the height will be automatically calculated

## 13.2.2.10 inner\_border

```
hpdf_border_style_t inner_border
```

Table inner border settings

#### 13.2.2.11 label\_cb

```
hpdftbl_content_callback_t label_cb
```

Table content callback. Will be called for each cell unless the cella has its own content callback

#### 13.2.2.12 label\_style

```
hpdf_text_style_t label_style
```

Label style settings

#### 13.2.2.13 outer\_border

```
hpdf_border_style_t outer_border
```

Table outer border settings

#### 13.2.2.14 pdf\_doc

HPDF\_Doc pdf\_doc

PDF document references

#### 13.2.2.15 pdf page

HPDF\_Page pdf\_page

PDF page reference

## 13.2.2.16 posx

HPDF\_REAL posx

X-position of table. Reference point defaults to lower left but can be changed by calling hpdftbl\_set\_anchor\_top\_left()

#### 13.2.2.17 posy

HPDF\_REAL posy

Y-position of table. Reference point defaults to lower left but can be changed by calling hpdftbl\_set\_anchor\_top\_left()

#### 13.2.2.18 rows

size\_t rows

Number of rows in table

Referenced by hpdftbl\_set\_col\_content\_style().

#### 13.2.2.19 tag

void\* tag

Optional tag used in callbacks. This can be used to identify the table or add any reference needed by a particular application

#### 13.2.2.20 title\_style

```
hpdf_text_style_t title_style
```

Title style

#### 13.2.2.21 title\_txt

```
char* title_txt
```

Title text

#### 13.2.2.22 use\_cell\_labels

```
_Bool use_cell_labels
```

Flag to determine if cell labels should be used

#### 13.2.2.23 use\_header\_row

```
_Bool use_header_row
```

Flag to determine if the first row in the table should be formatted as a header row

## 13.2.2.24 use\_label\_grid\_style

```
_Bool use_label_grid_style
```

Flag to determine of the short vertical label border should be used. Default is to use half grid.

#### 13.2.2.25 width

HPDF\_REAL width

Table width

The documentation for this struct was generated from the following file:

/Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

## 13.3 hpdftbl cell Struct Reference

Specification of individual cells in the table.

```
#include <hpdftbl.h>
```

#### **Data Fields**

- char \* label
- char \* content
- size\_t colspan
- size\_t rowspan
- HPDF\_REAL height
- HPDF\_REAL width
- HPDF REAL delta x
- HPDF REAL delta y
- · HPDF REAL textwidth
- hpdftbl\_content\_callback\_t content\_cb
- hpdftbl\_content\_callback\_t label\_cb
- hpdftbl\_content\_style\_callback\_t style\_cb
- hpdftbl\_canvas\_callback\_t canvas\_cb
- · hpdf text style t content style
- struct hpdftbl\_cell \* parent\_cell

## 13.3.1 Detailed Description

Specification of individual cells in the table.

This structure contains all information pertaining to each cell in the table. The position of the cell is given as relative position from the lower left corner of the table.

#### 13.3.2 Field Documentation

#### 13.3.2.1 canvas\_cb

```
hpdftbl_canvas_callback_t canvas_cb
```

Canvas callback. If this is specified then this will override any canvas callback specified for the table

## 13.3.2.2 colspan

size\_t colspan

Number of column this cell spans

#### 13.3.2.3 content

char\* content

String reference for cell content

## 13.3.2.4 content\_cb

```
{\tt hpdftbl\_content\_callback\_t\ content\_cb}
```

Content callback. If this is specified then this will override any content callback specified for the table

#### 13.3.2.5 content\_style

```
hpdf_text_style_t content_style
```

The style of the text content. If a style callback is specified the callback will override this setting

#### 13.3.2.6 delta\_x

```
HPDF_REAL delta_x
```

X-Position of cell from bottom left of table

## 13.3.2.7 delta\_y

```
HPDF_REAL delta_y
```

Y-Position of cell from bottom left of table

#### 13.3.2.8 height

HPDF\_REAL height

Height of cell

#### 13.3.2.9 label

char\* label

String reference for label text

## 13.3.2.10 label\_cb

```
hpdftbl_content_callback_t label_cb
```

Label callback. If this is specified then this will override any content callback specified for the table

#### 13.3.2.11 parent\_cell

```
struct hpdftbl_cell* parent_cell
```

Parent cell. If this cell is part of another cells row or column spanning this is a reference to this parent cell. Normal cells without spanning has NULL as parent cell.

## 13.3.2.12 rowspan

```
size_t rowspan
```

Number of rows this cell spans

#### 13.3.2.13 style\_cb

```
hpdftbl_content_style_callback_t style_cb
```

Style for content callback. If this is specified then this will override any style content callback specified for the table

#### 13.3.2.14 textwidth

HPDF\_REAL textwidth

Width of content string

## 13.3.2.15 width

HPDF\_REAL width

Width of cells

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

# 13.4 hpdftbl\_cell\_spec Struct Reference

Used in data driven table creation.

#include <hpdftbl.h>

## **Data Fields**

- size\_t row
- size\_t col
- unsigned rowspan
- · unsigned colspan
- char \* label
- hpdftbl\_content\_callback\_t content\_cb
- hpdftbl\_content\_callback\_t label\_cb
- hpdftbl\_content\_style\_callback\_t style\_cb
- hpdftbl\_canvas\_callback\_t canvas\_cb

## 13.4.1 Detailed Description

Used in data driven table creation.

A table can be specified by creating a array of this structure together with the hpdftbl\_spec\_t structure. The array should have one entry for each cell in the table.

See also

```
hpdftbl_stroke_from_data()
```

#### **Examples**

tut\_ex13\_2.c.

## 13.4.2 Field Documentation

#### 13.4.2.1 canvas cb

hpdftbl\_canvas\_callback\_t canvas\_cb

Canvas callback for this cell

### 13.4.2.2 col

size\_t col

Row for specified cell

#### 13.4.2.3 colspan

unsigned colspan

Number of columns the specified cell should span

#### 13.4.2.4 content\_cb

 ${\tt hpdftbl\_content\_callback\_t\ content\_cb}$ 

Content callback for this cell

#### 13.4.2.5 label

char\* label

The label for this cell

#### 13.4.2.6 label\_cb

hpdftbl\_content\_callback\_t label\_cb

Label callback for this cell

#### 13.4.2.7 row

size\_t row

Row for specified cell

Examples

tut\_ex13\_2.c.

## 13.4.2.8 rowspan

unsigned rowspan

Number of rows the specified cell should span

## 13.4.2.9 style\_cb

 ${\tt hpdftbl\_content\_style\_callback\_t~style\_cb}$ 

Content style callback for this cell

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

# 13.5 hpdftbl\_errcode\_entry Struct Reference

An entry in the error string table.

#### **Data Fields**

- char \* errstr
- · unsigned errcode

## 13.5.1 Detailed Description

An entry in the error string table.

#### 13.5.2 Field Documentation

#### 13.5.2.1 errcode

unsigned errcode

The error code from HPDF library

#### 13.5.2.2 errstr

char\* errstr

Pointer to the error string

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl\_errstr.c

# 13.6 hpdftbl\_spec Struct Reference

Used in data driven table creation.

#include <hpdftbl.h>

#### **Data Fields**

- char \* title
- · \_Bool use\_header
- · Bool use labels
- \_Bool use\_labelgrid
- size\_t rows
- size\_t cols
- HPDF\_REAL xpos
- HPDF REAL ypos
- HPDF\_REAL width
- HPDF\_REAL height
- hpdftbl\_content\_callback\_t content\_cb
- hpdftbl\_content\_callback\_t label\_cb
- hpdftbl\_content\_style\_callback\_t style\_cb
- hpdftbl\_callback\_t post\_cb
- hpdftbl\_cell\_spec\_t \* cell\_spec

## 13.6.1 Detailed Description

Used in data driven table creation.

This is used together with an array of cell specification hpdftbl\_cell\_spec\_t to specify the layout of a table.

#### **Examples**

```
tut_ex13_1.c, and tut_ex13_2.c.
```

#### 13.6.2 Field Documentation

#### 13.6.2.1 cell\_spec

```
hpdftbl_cell_spec_t* cell_spec
```

Array of cell specification

#### 13.6.2.2 cols

size\_t cols

Number of columns in the table

Referenced by hpdftbl\_stroke\_from\_data().

#### 13.6.2.3 content\_cb

hpdftbl\_content\_callback\_t content\_cb

Content callback for this table

## 13.6.2.4 height

HPDF\_REAL height

Height of table

#### 13.6.2.5 label\_cb

hpdftbl\_content\_callback\_t label\_cb

Label callback for this table

#### 13.6.2.6 post\_cb

hpdftbl\_callback\_t post\_cb

Post table creation callback. This is an opportunity for a client to do any special table manipulation before the table is stroked to the page. A reference to the table will be passed on in the callback.

## 13.6.2.7 rows

size\_t rows

Number of rows in the table

Referenced by hpdftbl\_stroke\_from\_data().

#### 13.6.2.8 style\_cb

hpdftbl\_content\_style\_callback\_t style\_cb

Content style callback for table

## 13.6.2.9 title

char\* title

Table title

**Examples** 

tut\_ex13\_1.c, and tut\_ex13\_2.c.

Referenced by hpdftbl\_stroke\_from\_data().

#### 13.6.2.10 use\_header

\_Bool use\_header

Use a header for the table

## 13.6.2.11 use\_labelgrid

\_Bool use\_labelgrid

Use label grid in table

#### 13.6.2.12 use\_labels

\_Bool use\_labels

Use labels in table

#### 13.6.2.13 width

HPDF\_REAL width

Width of table

#### 13.6.2.14 xpos

HPDF\_REAL xpos

X-position for table

#### 13.6.2.15 ypos

HPDF\_REAL ypos

Y-position for table

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

## 13.7 hpdftbl\_theme Struct Reference

Define a set of styles into a table theme.

```
#include <hpdftbl.h>
```

#### **Data Fields**

```
• hpdf_text_style_t * content_style
```

- hpdf\_text\_style\_t \* label\_style
- hpdf\_text\_style\_t \* header\_style
- hpdf\_text\_style\_t \* title\_style
- hpdf\_border\_style\_t \* inner\_border
- hpdf\_border\_style\_t \* outer\_border
- \_Bool use\_labels
- \_Bool use\_label\_grid\_style
- \_Bool use\_header\_row

## 13.7.1 Detailed Description

Define a set of styles into a table theme.

Contains all information about the styles of various elements in the table that together make up the table style

#### 13.7.2 Field Documentation

## 13.7.2.1 content\_style

```
hpdf_text_style_t* content_style
```

Content text style

## 13.7.2.2 header\_style

```
hpdf_text_style_t* header_style
```

Header text style

## 13.7.2.3 inner\_border

```
hpdf_border_style_t* inner_border
```

Table inner border style

#### 13.7.2.4 label\_style

```
hpdf_text_style_t* label_style
```

Label text style

#### 13.7.2.5 outer\_border

```
hpdf_border_style_t* outer_border
```

Table outer border style

## 13.7.2.6 title\_style

```
hpdf_text_style_t* title_style
```

Table title text style

## 13.7.2.7 use\_header\_row

```
_Bool use_header_row
```

Flag if header row should be used

#### 13.7.2.8 use\_label\_grid\_style

```
_Bool use_label_grid_style
```

Flag if the special short vertical grid style for labels should be used

#### 13.7.2.9 use\_labels

```
_Bool use_labels
```

Flag if cell labels should be used

The documentation for this struct was generated from the following file:

/Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

# 13.8 line\_dash\_style Struct Reference

Definition of a dashed line style.

#### **Data Fields**

- HPDF\_UINT16 dash\_ptn [8]
- size\_t num

## 13.8.1 Detailed Description

Definition of a dashed line style.

## 13.8.2 Field Documentation

## 13.8.2.1 dash\_ptn

```
HPDF_UINT16 dash_ptn[8]
```

HPDF ash line definition

#### 13.8.2.2 num

```
size_t num
```

Number of segments in the dashed line

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl.c

## 13.9 text\_style Struct Reference

Specification of a text style.

```
#include <hpdftbl.h>
```

### **Data Fields**

- char \* font
- HPDF\_REAL fsize
- HPDF\_RGBColor color
- HPDF\_RGBColor background
- hpdftbl\_text\_align\_t halign

### 13.9.1 Detailed Description

Specification of a text style.

This structure collects the basic properties for a text string (font, color, background, horizontal alignment)

**Examples** 

tut ex09.c.

### 13.9.2 Field Documentation

### 13.9.2.1 background

HPDF\_RGBColor background

Font background color

**Examples** 

tut\_ex09.c.

#### 13.9.2.2 color

HPDF\_RGBColor color

Font color

**Examples** 

tut\_ex09.c.

### 13.9.2.3 font

char\* font

Font face name

Examples

tut\_ex09.c.

#### 13.9.2.4 fsize

HPDF\_REAL fsize

Font size

**Examples** 

tut\_ex09.c.

### 13.9.2.5 halign

```
hpdftbl_text_align_t halign
```

Text horizontal alignment

Examples

tut\_ex09.c.

The documentation for this struct was generated from the following file:

• /Users/ljp/Devel/hpdf\_table/src/hpdftbl.h

# **Chapter 14**

# **File Documentation**

## 14.1 config.h

```
1 /* src/config.h. Generated from config.h.in by configure.
2 /* src/config.h.in. Generated from configure.ac by autoheader. \star/
4 /* Define to 1 if you have the <dlfcn.h> header file. */ 5 #define HAVE_DLFCN_H 1
7 /* Define to 1 if you have the <hpdf.h> header file. \star/
8 #define HAVE_HPDF_H
10 /\star Define to 1 if you have the <iconv.h> header file. \star/
11 #define HAVE_ICONV_H 1
12
13 /* Define to 1 if you have the <inttypes.h> header file. */
14 #define HAVE_INTTYPES_H 1
16 /* Define to 1 if you have the 'hpdf' library (-lhpdf). */
17 #define HAVE_LIBHPDF 1
18
19 /* Define to 1 if you have the 'iconv' library (-liconv). */
20 #define HAVE_LIBICONV 1
22 /\star Define to 1 if you have the <stdint.h> header file. \star/
23 #define HAVE_STDINT_H 1
24
25 /* Define to 1 if you have the <stdio.h> header file. */
26 #define HAVE_STDIO_H 1
28 /* Define to 1 if you have the <stdlib.h> header file. \star/
29 #define HAVE STDLIB H 1
30
31 /* Define to 1 if you have the <strings.h> header file. */
32 #define HAVE_STRINGS_H 1
34 /* Define to 1 if you have the <string.h> header file. */
35 #define HAVE_STRING_H 1
36
37 /* Define to 1 if you have the <sys/stat.h> header file. */
38 #define HAVE_SYS_STAT_H 1
40 /\star Define to 1 if you have the <sys/types.h> header file. \star/
41 #define HAVE_SYS_TYPES_H 1
42
43 /* Define to 1 if you have the <unistd.h> header file. \star/
44 #define HAVE_UNISTD_H 1
46 /* True if system type is Apple OSX */
47 #define IS_OSX 1
49 /\star Define to the sub-directory where libtool stores uninstalled libraries. \star/
50 #define LT_OBJDIR ".libs/"
52 /* Name of package */
53 #define PACKAGE "libhpdftbl"
55 /* Define to the address where bug reports for this package should be sent. \star/ 56 #define PACKAGE_BUGREPORT "johan162@gmail.com"
58 /\star Define to the full name of this package. \star/
```

```
59 #define PACKAGE_NAME "libhpdftbl"
61 /\star Define to the full name and version of this package. \star/
62 #define PACKAGE_STRING "libhpdftbl 1.0.0-beta"
6.3
64 /\star Define to the one symbol short name of this package. \star/
65 #define PACKAGE_TARNAME "libhpdftbl"
67 /\star Define to the home page for this package. \star/
68 #define PACKAGE_URL "
69
70 /\star Define to the version of this package. \star/
71 #define PACKAGE_VERSION "1.0.0-beta"
73 /\star Define to 1 if all of the C90 standard headers exist (not just the ones
      required in a freestanding environment). This macro is provided for
75
      backward compatibility; new code need not use it. */
76 #define STDC_HEADERS 1
78 /* Version number of package */
79 #define VERSION "1.0.0-beta"
```

## 14.2 /Users/ljp/Devel/hpdf\_table/src/hpdftbl.c File Reference

Main source module for hpdftbl.

```
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <string.h>
#include <iconv.h>
#include <hpdf.h>
#include "hpdftbl.h"
```

### **Data Structures**

· struct line dash style

Definition of a dashed line style.

### **Macros**

- #define TRUE 1
- · #define FALSE 0
- #define \_IDX(r, c) (r\*t->cols+c)
- #define HPDFTBL\_DEFAULT\_TITLE\_STYLE (hpdf\_text\_style\_t){HPDF\_FF\_HELVETICA\_BOLD,11,(HPDF← \_RGBColor){0,0,0},(HPDF\_RGBColor){0.9f,0.9f,0.9f}, LEFT}
- #define HPDFTBL\_DEFAULT\_HEADER\_STYLE (hpdf\_text\_style\_t){HPDF\_FF\_HELVETICA\_BOLD,10,(HPDF← \_RGBColor){0,0,0},(HPDF\_RGBColor){0.9f,0.9f,0.9f}, CENTER}
- #define **HPDFTBL\_DEFAULT\_LABEL\_STYLE** (hpdf\_text\_style\_t){HPDF\_FF\_TIMES\_ITALIC,9,(HPDF\_  $\leftarrow$  RGBColor){0.4f,0.4f,0.4f},(HPDF\_RGBColor){1,1,1}, LEFT}
- #define HPDFTBL\_DEFAULT\_CONTENT\_STYLE (hpdf\_text\_style\_t){HPDF\_FF\_COURIER,10,(HPDF\_← RGBColor){0.2f,0.2f},0.2f},(HPDF\_RGBColor){1,1,1}, LEFT}
- #define HPDFTBL\_DEFAULT\_INNER\_BORDER\_STYLE (hpdf\_border\_style\_t){0.7f, (HPDF\_RGBColor){0. ←
  5f,0.5f,0.5f},0}
- #define **HPDFTBL\_DEFAULT\_OUTER\_BORDER\_STYLE** (hpdf\_border\_style\_t){1.0f, (HPDF\_RGBColor){0.← 2f,0.2f,0.2f},0}
- #define \_SET\_ERR(t, err, r, c) do {err\_code=err;err\_row=r;err\_col=c; if(hpdftbl\_err\_handler){hpdftbl\_err\_← handler(t,r,c,err);}} while(0)
- $\bullet \quad \text{\#define } \_\textbf{CHK\_TABLE}(t) \text{ do } \{ \text{if(NULL} == t) \ \{ \text{err\_code=-3;err\_row=-1;err\_col=-1;return -1;} \} \text{ while(0)} \\$
- #define ERR\_UNKNOWN 11

### **Typedefs**

typedef struct line\_dash\_style line\_dash\_style\_t

Definition of a dashed line style.

### **Functions**

• int hpdftbl\_set\_line\_dash (hpdftbl\_t t, hpdftbl\_line\_style\_t style)

Internal helper to set the line style.

• void hpdftbl\_set\_anchor\_top\_left (const \_Bool anchor)

Switch stroking anchor point.

Bool hpdftbl get anchor top left (void)

Get stroking anchor point.

const char \* hpdftbl get errstr (int err)

Translate a table error code to a human readable string.

void hpdftbl default table error handler (hpdftbl t t, int r, int c, int err)

A simple default table error handler callback that outputs the error to stderr in human readable format and quits the process.

• int hpdftbl\_get\_last\_errcode (const char \*\*errstr, int \*row, int \*col)

Return last error code.

• hpdftbl\_error\_handler\_t hpdftbl\_set\_errhandler (hpdftbl\_error\_handler\_t err\_handler)

Specify errhandler for the table routines.

void hpdftbl\_set\_text\_encoding (char \*target, char \*source)

Determine text source encoding.

• int hpdftbl\_encoding\_text\_out (HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL ypos, char \*text)

Strke text with current encoding.

 void HPDF\_RoundedCornerRectangle (HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL ypos, HPDF— \_REAL width, HPDF\_REAL height, HPDF\_REAL rad)

Draw rectangle with rounded corner.

hpdftbl\_theme\_t \* hpdftbl\_get\_default\_theme (void)

Return the default theme.

• int hpdftbl\_destroy\_theme (hpdftbl\_theme\_t \*theme)

Destroy existing theme structure and free memory.

hpdftbl\_t hpdftbl\_create (size\_t rows, size\_t cols)

Create a new table with no title.

hpdftbl\_t hpdftbl\_create\_title (size\_t rows, size\_t cols, char \*title)

Create a new table with title top row.

• int hpdftbl\_set\_colwidth\_percent (hpdftbl\_t t, size\_t c, float w)

Set column width as percentage of overall table width.

• int hpdftbl\_set\_outer\_border (hpdftbl\_t t, HPDF\_REAL width, HPDF\_RGBColor color)

Specify style for table outer border.

• int hpdftbl\_set\_inner\_border (hpdftbl\_t t, HPDF\_REAL width, HPDF\_RGBColor color)

Specify style for table inner border.

int hpdftbl\_set\_header\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_

RGBColor background)

Specify style for table heder row.

int hpdftbl\_set\_background (hpdftbl\_t t, HPDF\_RGBColor background)

Set table background color.

• int hpdftbl set header halign (hpdftbl tt, hpdftbl text align talign)

Set table header text align.

int hpdftbl\_use\_header (hpdftbl\_t t, \_Bool use)

- int hpdftbl\_use\_labels (hpdftbl\_t t, \_Bool use)
- int hpdftbl\_use\_labelgrid (hpdftbl\_t t, \_Bool use)
- int hpdftbl\_set\_tag (hpdftbl\_t t, void \*tag)

Set an optional tag for the table.

int hpdftbl destroy (hpdftbl t t)

Destroy a table and free all memory.

• int hpdftbl set cell (hpdftbl t t, int r, int c, char \*label, char \*content)

Set content for specific cell.

• int hpdftbl\_set\_cellspan (hpdftbl\_t t, size\_t r, size\_t c, size\_t rowspan, size\_t colspan)

Set cell spanning.

int hpdftbl\_clear\_spanning (hpdftbl\_t t)

Clear all cell spanning.

• int hpdftbl\_set\_content\_cb (hpdftbl\_t t, hpdftbl\_content\_callback\_t cb)

Set table content callback.

• int hpdftbl set cell content cb (hpdftbl tt, size tr, size tc, hpdftbl content callback tcb)

Set cell content callback.

• int hpdftbl\_set\_cell\_label\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_content\_callback\_t cb)

Set cell label callback.

• int hpdftbl\_set\_cell\_canvas\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_canvas\_callback\_t cb)

Set cell canvas callback.

int hpdftbl\_set\_label\_cb (hpdftbl\_t t, hpdftbl\_content\_callback\_t cb)

Set table label callback.

int hpdftbl\_set\_canvas\_cb (hpdftbl\_t t, hpdftbl\_canvas\_callback\_t cb)

Set cell canvas callback.

int hpdftbl\_set\_labels (hpdftbl\_t t, char \*\*labels)

Set the text for the cell labels.

• int hpdftbl\_set\_content (hpdftbl\_t t, char \*\*content)

Set the content for the table.

 int hpdftbl\_set\_label\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_← RGBColor background)

Set the font style for labels.

int hpdftbl\_set\_content\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_

RGBColor background)

Set font style for text content.

 int hpdftbl\_set\_row\_content\_style (hpdftbl\_t t, size\_t r, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_RGBColor background)

Set the font style for an entire row of cells.

 int hpdftbl\_set\_col\_content\_style (hpdftbl\_t t, size\_t c, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_RGBColor background)

Set the font style for an entre column of cells.

int hpdftbl\_set\_cell\_content\_style (hpdftbl\_t t, size\_t r, size\_t c, char \*font, HPDF\_REAL fsize, HPDF\_

RGBColor color, HPDF\_RGBColor background)

Set the font style for content of specified cell.

• int hpdftbl\_set\_cell\_content\_style\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_content\_style\_callback\_t cb)

Set cell specific callback to specify cell content style.

• int hpdftbl\_set\_content\_style\_cb (hpdftbl\_t t, hpdftbl\_content\_style\_callback\_t cb)

Set callback to specify cell content style.

• int hpdftbl\_set\_title\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_← RGBColor background)

Set the table title style.

• int hpdftbl set title (hpdftbl tt, char \*title)

Set table title.

int hpdftbl\_set\_title\_halign (hpdftbl\_t t, hpdftbl\_text\_align\_t align)

Set horizontal alignment for table title.

• int hpdftbl\_apply\_theme (hpdftbl\_t t, hpdftbl\_theme\_t \*theme)

Apply a specified theme to a table.

• int hpdftbl\_stroke\_from\_data (HPDF\_Doc pdf\_doc, HPDF\_Page pdf\_page, hpdftbl\_spec\_t \*tbl\_spec, hpdftbl\_theme\_t \*theme)

Construct the table from a array specification.

• int hpdftbl\_get\_last\_auto\_height (HPDF\_REAL \*height)

Get the height calculated for the last constructed table.

• int hpdftbl\_stroke (HPDF\_Doc pdf, const HPDF\_Page page, hpdftbl\_t t, const HPDF\_REAL xpos, const HPDF\_REAL width, HPDF\_REAL height)

Stroke the table.

### 14.2.1 Detailed Description

Main source module for hpdftbl.

#### 14.2.2 Function Documentation

### 14.2.2.1 HPDF\_RoundedCornerRectangle()

Draw rectangle with rounded corner.

Draw a rectangle with rounded corner with the current line width, color. The rectangle will not be stroked.

#### **Parameters**

page	Page handle	
xpos	Lower left x-position of rectangle	
ypos	Lower left y-position of rectangle	
width	Width of rectangle	
height	Height of rectangle	
rad	Radius of corners	

Referenced by hpdftbl widget slide button().

### 14.2.2.2 hpdftbl\_apply\_theme()

Apply a specified theme to a table.

Apply a specified theme to a table. The default table can be retrieved with hpdftbl\_get\_default\_theme()

### **Parameters**

t	Table handle
theme	Theme reference

### Returns

0 on success, -1 on failure

#### See also

hpdftbl\_get\_default\_theme()

### 14.2.2.3 hpdftbl\_clear\_spanning()

```
int hpdftbl_clear_spanning ( \label{eq:hpdftbl_t} \operatorname{hpdftbl_t} t \ t \ )
```

Clear all cell spanning.

Reset all spanning cells to no spanning

### **Parameters**

t Table handle

#### Returns

0 on success, -1 on failure

#### See also

hpdftbl\_set\_cellspan()

### 14.2.2.4 hpdftbl\_create()

Create a new table with no title.

Create a new table structure. This is the basic handler needed for most other API functions.

#### **Parameters**

rows	Number of rows
cols	Number of columns

#### Returns

A handle to a table, NULL in case of OOM

#### **Examples**

```
tut_ex01.c, tut_ex02.c, tut_ex03.c, tut_ex09.c, tut_ex10.c, tut_ex11.c, and tut_ex12.c.
```

### 14.2.2.5 hpdftbl\_create\_title()

Create a new table with title top row.

Create a new table structure. This is the basic handler needed for most other API functions.

#### **Parameters**

rows	Number of rows
cols	Number of columns
title	Title of table

### Returns

A handle to a table, NULL in case of OOM

### **Examples**

```
tut_ex05.c, tut_ex06.c, tut_ex07.c, and tut_ex08.c.
```

 $Referenced \ by \ hpdftbl\_create(), \ and \ hpdftbl\_stroke\_from\_data().$ 

### 14.2.2.6 hpdftbl\_default\_table\_error\_handler()

A simple default table error handler callback that outputs the error to stderr in human readable format and quits the process.

#### **Parameters**

t	Table where the error happened (can be NULL)
r	Cell row
С	Cell column
err	The error code

#### **Examples**

tut\_ex10.c, tut\_ex11.c, and tut\_ex12.c.

### 14.2.2.7 hpdftbl\_destroy()

```
int hpdftbl_destroy ( \begin{array}{c} & \text{hpdftbl\_t } t \end{array})
```

Destroy a table and free all memory.

Destroy a table previous created with table\_create()

#### **Parameters**

```
t Handle to table
```

#### Returns

0 on success, -1 on failure

### 14.2.2.8 hpdftbl\_destroy\_theme()

Destroy existing theme structure and free memory.

Free all memory allocated by a theme

#### **Parameters**

theme The theme to free
-------------------------

### 14.2.2.9 hpdftbl\_encoding\_text\_out()

Strke text with current encoding.

Utility function to stroke text with character encoding. It is the calling routines responsibility to enclose text in a HPDF\_Page\_BeginText() / HPDF\_Page\_EndText()

#### **Parameters**

page	Page handle
xpos	X coordinate
ypos	Y coordinate
text	Text to print

#### Returns

-1 on error, 0 on success

### 14.2.2.10 hpdftbl\_get\_anchor\_top\_left()

```
_Bool hpdftbl_get_anchor_top_left ( void )
```

Get stroking anchor point.

Get base point for table positioning. By default the top left is used.

#### See also

hpdftbl\_set\_anchor\_top\_left

#### 14.2.2.11 hpdftbl\_get\_default\_theme()

Return the default theme.

Create and return a theme corresponding to the default table theme. It is the calling functions responsibility to call <a href="hpdftbl\_destroy\_theme">hpdftbl\_destroy\_theme</a>() to free the allocated memory. The default theme is a good starting point to just make minor modifications without having to define all elements.

#### Returns

A new theme initialized to the default settings

#### See also

hpdftbl\_apply\_theme()

### 14.2.2.12 hpdftbl\_get\_errstr()

Translate a table error code to a human readable string.

The function returns a pointer to a static string that cannot be modified. It will translate both internal table error messages as well as generic HPDF library error codes.

#### **Parameters**

err code The error code t	to be translated
---------------------------	------------------

#### Returns

Static pointer to string for valid error code, NULL otherwise

### See also

```
hpdftbl_hpdf_get_errstr()
```

Referenced by hpdftbl\_default\_table\_error\_handler(), and hpdftbl\_get\_last\_errcode().

#### 14.2.2.13 hpdftbl\_get\_last\_auto\_height()

```
int hpdftbl_get_last_auto_height ( \label{eq:hpdf} \texttt{HPDF\_REAL} \, * \, height \, )
```

Get the height calculated for the last constructed table.

Get the last automatically calculated heigh when stroking a table. (The height will be automatically calculated if it was specified as 0)

#### **Parameters**

#### Returns

-1 on error, 0 if successful

#### 14.2.2.14 hpdftbl\_get\_last\_errcode()

Return last error code.

Return last error code. if errstr is not NULL a human readable string describing the error will be copied to the string. The error code will be reset after call.

#### **Parameters**

errstr	A string buffer where the error string is written to
row	The row where the error was found
col	The col where the error was found

#### Returns

The last error code

### 14.2.2.15 hpdftbl\_set\_anchor\_top\_left()

Switch stroking anchor point.

Set anchor point for table positioning. By default the top left is used as anchor. Calling this function with FALSE can set the basepoint to bottom left instead.

#### **Parameters**

anchor Set to TRUE to use top left as anchor, FALSE for bot
---

### 14.2.2.16 hpdftbl\_set\_background()

Set table background color.

Set table background

#### **Parameters**

t	Table handle
background	Background color

#### Returns

0 on success, -1 on failure

### 14.2.2.17 hpdftbl\_set\_canvas\_cb()

Set cell canvas callback.

Set cell canvas callback. This callback gets called for each cell in the table. The purpose is to allow the client to add dynamic content to the specified cell. The callback is made before the cell border and content is drawn making it possible to for example add a background color to individual cells. The callback function will receive the Table tag, the row and column, the x, y position of the lower left corner of the table and the width and height of the cell. To set the canvas callback only for a sepcific cell use the hpdftbl\_set\_cell\_canvas\_callback() function

#### **Parameters**

t	Table handle
cb	Callback function

#### Returns

-1 on failure, 0 otherwise

#### See also

```
hpdftbl_set_cell_canvas_cb()
```

### 14.2.2.18 hpdftbl\_set\_cell()

```
int hpdftbl_set_cell (
          hpdftbl_t t,
          int r,
          int c,
          char * label,
          char * content )
```

Set content for specific cell.

Set label and content for a specific cell. If the specified cell is part of another cells spanning then error is given (returns -1),

#### **Parameters**

t	Table handle
r	Row
С	Column
label	Label
content	Text content

### Returns

-1 on error, 0 if successful

#### **Examples**

tut\_ex01.c, and tut\_ex03.c.

#### 14.2.2.19 hpdftbl set cell canvas cb()

```
int hpdftbl_set_cell_canvas_cb (
          hpdftbl_t t,
          size_t r,
          size_t c,
          hpdftbl_canvas_callback_t cb )
```

Set cell canvas callback.

Set a canvas callback for an individual cell. This will override the table canvas callback. The canvas callback is called with arguments that give the bounding box for the cell. In that way a callback function may draw arbitrary graphic in the cell. The callback is made before the cell border and content is drawn making it possible to for example add a background color to individual cells. The callback function will receive the Table tag, the row and column, the x, y position of the lower left corner of the table and the width and height of the cell.

### **Parameters**

t	Table handle
r	Cell row
С	Cell column
cb	Callback function

### Returns

-1 on failure, 0 otherwise

### See also

```
hpdftbl_canvas_callback_t
hpdftbl_set_canvas_callback
```

### 14.2.2.20 hpdftbl\_set\_cell\_content\_cb()

```
int hpdftbl_set_cell_content_cb (
          hpdftbl_t t,
          size_t r,
          size_t c,
          hpdftbl_content_callback_t cb )
```

Set cell content callback.

Set a content callback for an individual cell. This will override the table content callback.

### **Parameters**

t	Table handle
cb	Callback function
r	Cell row
С	Cell column

### Returns

-1 on failure, 0 otherwise

### See also

```
hpdftbl_set_content_cb()
```

### **Examples**

```
tut_ex06.c, tut_ex07.c, and tut_ex08.c.
```

#### 14.2.2.21 hpdftbl\_set\_cell\_content\_style()

```
int hpdftbl_set_cell_content_style (
    hpdftbl_t t,
    size_t r,
    size_t c,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set the font style for content of specified cell.

SSet the font style for content of specified cell. This will override the global cell content setting.

#### **Parameters**

t	Table handle
r	Cell row
С	Cell column
font	Font name
fsize	Font size
color	Color
background	Background color

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_set_content_style()
hpdftbl_set_cell_content_style_cb()
```

Referenced by hpdftbl\_set\_col\_content\_style(), and hpdftbl\_set\_row\_content\_style().

### 14.2.2.22 hpdftbl\_set\_cell\_content\_style\_cb()

Set cell specific callback to specify cell content style.

Set callback to format the style for the specified cell

### **Parameters**

t	Table handle
r	Cell row
С	Cell column
cb	Callback function

### Returns

0 on success, -1 on failure

### See also

hpdftbl\_set\_ontent\_style\_cb()

### 14.2.2.23 hpdftbl\_set\_cell\_label\_cb()

```
int hpdftbl_set_cell_label_cb (
          hpdftbl_t t,
          size_t r,
          size_t c,
          hpdftbl_content_callback_t cb )
```

Set cell label callback.

Set a label callback for an individual cell. This will override the table content callback.

#### **Parameters**

t	Table handle
cb	Callback function
r	Cell row
С	Cell column

### Returns

-1 on failure, 0 otherwise

### See also

hpdftbl\_set\_label\_cb()

### 14.2.2.24 hpdftbl\_set\_cellspan()

Set cell spanning.

Set row and column spanning for a cell

#### **Parameters**

t	Table handle
r	Row
С	Column
rowspan	Row span
colspan	Column span

#### Returns

-1 on error, 0 if successful

### See also

hpdftbl\_clear\_spanning()

#### **Examples**

tut\_ex07.c, and tut\_ex08.c.

#### 14.2.2.25 hpdftbl\_set\_col\_content\_style()

```
int hpdftbl_set_col_content_style (
    hpdftbl_t t,
    size_t c,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set the font style for an entre column of cells.

Set font options for the specified column of cells. This will override the global cell content setting.

t	Table handle	
С	Column to affect	
Ge <b>้าง</b> ematted on Mon A	Ap <b>F25</b> 02102020160€1:42 for libh	pdftbl by Doxygen
fsize	Font size	
color	Color	
background	Background color	

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_set_content_style()
hpdftbl_set_cell_content_style_cb()
```

### 14.2.2.26 hpdftbl\_set\_colwidth\_percent()

```
int hpdftbl_set_colwidth_percent (
          hpdftbl_t t,
          size_t c,
          float w )
```

Set column width as percentage of overall table width.

Specify column width as percentage of total column width. Note that this will only take effect if the table has an overall width specified when stroked.

#### **Parameters**

t	Table handle
С	Column to set width of first column has index 0
W	Width as percentage in range [0.0, 100.0]

#### Returns

0 on success, -1 on failure

#### **Examples**

```
tut_ex08.c, tut_ex09.c, tut_ex10.c, tut_ex11.c, and tut_ex12.c.
```

#### 14.2.2.27 hpdftbl\_set\_content()

Set the content for the table.

Set content for all cells. It is the calling functions responsibility that the content array is big enough to cover the entire table. The string array corresponds to a flattened 2-d array and the label for cell (r,c) is calculated as  $(r*num\_cols+c)$  where num\\_cols is the number of columns in the table. It is allowed to specify NULL as placeholder for empty labels. The actual text in the table will be allocated with strdup() so it is safe to free the memory for the labels after the call to this function. Please note that even if the table contains spanning cells the content data must include empty data for covered cells. For a N x M table the data must have (N\*M) entries. Another way to specify the content is to use the callback mechanism. By setting up a content callback function that returns the content for a cell

#### **Parameters**

t	Table handle
content	A one dimensional string array of content string

#### Returns

-1 on error, 0 if successful

### See also

```
hpdftbl_set_content_callback()
hpdftbl_set_cell_content_callback()
```

### **Examples**

tut\_ex02.c, tut\_ex05.c, tut\_ex10.c, tut\_ex11.c, and tut\_ex12.c.

### 14.2.2.28 hpdftbl\_set\_content\_cb()

Set table content callback.

Set content callback. This callback gets called for each cell in the table and the returned string will be used as the content. The string will be duplicated so it is safe for a client to reuse the string space. If NULL is returned from the callback then the content will be set to the content specified with the direct content setting. The callback function will receive the Table tag and the row and column

#### **Parameters**

t	Table handle
cb	Callback function

#### See also

```
hpdftbl_set_cell_content_cb()
```

### **Examples**

tut\_ex06.c, tut\_ex07.c, tut\_ex08.c, and tut\_ex09.c.

#### 14.2.2.29 hpdftbl\_set\_content\_style()

```
int hpdftbl_set_content_style (
          hpdftbl_t t,
          char * font,
          HPDF_REAL fsize,
          HPDF_RGBColor color,
          HPDF_RGBColor background )
```

Set font style for text content.

Set font options for cell content. This will be applied for all cells in the table.

#### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Color
background	Background color

#### Returns

-1 on error, 0 if successful

### See also

```
hpdftbl_set_cell_content_style()
hpdftbl_set_cell_content_style_cb()
```

### 14.2.2.30 hpdftbl\_set\_content\_style\_cb()

```
int hpdftbl_set_content_style_cb ( \label{eq:hpdftbl_t} \mbox{ hpdftbl_t } \mbox{ } t, $$ \mbox{hpdftbl_content_style_callback_t } \mbox{ } cb \mbox{ )}
```

Set callback to specify cell content style.

Set callback to format the style for cells in the table. If a cell has its own content style callback that callback will override the generic table callback.

t	Table handle
cb	Callback function

Returns

0 on success, -1 on failure

See also

```
hpdftbl_set_cell_content_style_cb()
```

**Examples** 

tut\_ex09.c.

### 14.2.2.31 hpdftbl\_set\_errhandler()

Specify errhandler for the table routines.

**Parameters** 

```
err_handler
```

Returns

The old error handler or NULL if non exists

Examples

```
tut_ex10.c, tut_ex11.c, and tut_ex12.c.
```

### 14.2.2.32 hpdftbl\_set\_header\_halign()

Set table header text align.

Set horizontal text alignment for header row

t	Table handle
align	Alignment

#### Returns

0 on success, -1 on failure

### 14.2.2.33 hpdftbl\_set\_header\_style()

```
int hpdftbl_set_header_style (
          hpdftbl_t t,
          char * font,
          HPDF_REAL fsize,
          HPDF_RGBColor color,
          HPDF_RGBColor background )
```

Specify style for table heder row.

Set the font properties and background for the header row which is the top row if enabled. The header row will be automatically enabled after calling this function. The header can be enabled/disabled separately with hpdftbl\_use\_header()

### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Font color
background	Cell background color

#### Returns

0 on success, -1 on failure hpdftbl\_use\_header()

#### 14.2.2.34 hpdftbl\_set\_inner\_border()

Specify style for table inner border.

Set inner border properties

t	Table handle
width	Line width
color	Line color

#### Returns

0 on success, -1 on failure

### 14.2.2.35 hpdftbl\_set\_label\_cb()

```
int hpdftbl_set_label_cb ( \label{eq:hpdftbl_t} \mbox{hpdftbl_t } t \mbox{,} \\ \mbox{hpdftbl\_content\_callback\_t } cb \mbox{ )}
```

Set table label callback.

Set label callback. This callback gets called for each cell in the table and the returned string will be used as the label. The string will be duplicated so it is safe for a client to reuse the string space. If NULL is returned from the callback then the label will be set to the content specified with the direct label setting. The callback function will receive the Table tag and the row and column

#### **Parameters**

t	Table handle
cb	Callback function

### Returns

-1 on failure, 0 otherwise

### See also

```
hpdftbl_content_callback_t
hpdftbl_set_cell_label_cb()
```

### **Examples**

tut\_ex06.c, tut\_ex07.c, and tut\_ex08.c.

### 14.2.2.36 hpdftbl\_set\_label\_style()

Set the font style for labels.

Set font, color and background options for cell labels.

#### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Color
background	Background color

#### Returns

-1 on error, 0 if successful

#### 14.2.2.37 hpdftbl\_set\_labels()

Set the text for the cell labels.

Set labels for all the cell. It is the calling functions responsibility that the labels array is big enough to cover the entire table. The string array corresponds to a flattened 2-d array and the label for cell (r,c) is calculated as  $(r*num\_cols+c)$  where  $num\_cols$  is the number of columns in the table. It is allowed to specify NULL as placeholder for empty labels. The actual text in the table will be allocated with strdup() so it is safe to free the memory for the labels after the call to this function. Please note that even if the table contains spanning cells the content data must include empty data for covered cells. For a N x M table the data must have (N\*M) entries.

### Parameters

t	Table handle
labels	A one dimensional string array of labels

#### Returns

-1 on error, 0 if successful

### See also

```
hpdftbl_set_cell_label_cb()
hpdftbl_set_label_cb()
```

### Examples

tut\_ex05.c.

### 14.2.2.38 hpdftbl\_set\_line\_dash()

Internal helper to set the line style.

The drawing of a dashed line uses the undrlying HPDF function HPDF\_Page\_SetDash()

### **Parameters**

t	Table handle
style	

### Returns

-1 on error, 0 on success

#### See also

line\_dash\_style

### 14.2.2.39 hpdftbl\_set\_outer\_border()

Specify style for table outer border.

Set outer border properties

#### **Parameters**

t	Table handle
width	Line width
color	Line color

### Returns

0 on success, -1 on failure

#### 14.2.2.40 hpdftbl\_set\_row\_content\_style()

```
int hpdftbl_set_row_content_style (
    hpdftbl_t t,
    size_t r,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set the font style for an entire row of cells.

Set font options for the specified row of cells. This will override the global cell content .

#### **Parameters**

t	Table handle
r	Row to affect
font	Font name
fsize	Font size
color	Color
background	Background color

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_set_content_style()
hpdftbl_set_cell_content_style_cb()
```

### 14.2.2.41 hpdftbl\_set\_tag()

```
int hpdftbl_set_tag ( \begin{array}{c} & \text{hpdftbl\_t } t \text{,} \\ & \text{void} * tag \end{array})
```

Set an optional tag for the table.

Set an optional tag in the table. The tag can be a pointer to anything. The tag is passed as the first argument in the various callbacks and can be used to supply table specific information or identify a specific table in the case the same callback is used for multiple tables.

t	The table handle
tag	The tag (pointer to any object)

#### Returns

0 on success, -1 on failure

### 14.2.2.42 hpdftbl\_set\_text\_encoding()

Determine text source encoding.

The default HPDF encoding is a standard PDF encoding. The problem with that is that now almost 100% of all code is written in UTF-8 encoding and trying to print text strings with accented charactes will simply not work. For example the default encoding assumes that strings are given in UTF-8 and sets the target to ISO8859-4 which includes northern europe accented characters. The conversion is internally handled by the standard iconv() routines.

#### **Parameters**

target	The target encoding. See HPDF documentation for supported encodings.
source	The source encodings, i.e. what encodings are sth strings in the source specified in.

### 14.2.2.43 hpdftbl\_set\_title()

Set table title.

Set table title

### Parameters

t	Table handle
title	Title string

#### Returns

0 on success, -1 on failure

### See also

```
hpdftbl_set_title_style()
hpdftbl_set_title_halign()
```

### 14.2.2.44 hpdftbl\_set\_title\_halign()

Set horizontal alignment for table title.

Set horizontal text alignment for title

### **Parameters**

t	Table handle
align	Alignment

### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_set_title()
hpdftbl_set_title_style()
```

### 14.2.2.45 hpdftbl\_set\_title\_style()

```
int hpdftbl_set_title_style (
    hpdftbl_t t,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set the table title style.

Set font options for title

#### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Color
background	Background color

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_set_title()
hpdftbl_set_title_halign()
```

### 14.2.2.46 hpdftbl\_stroke()

Stroke the table.

Stroke the table at the specified position and size. The position is by default specified as the upper left corner of the table. Use the hpdftbl\_set\_origin\_top\_left(FALSE) to use the bottom left of the table as reference point.

#### **Parameters**

pdf	The HPDF document handle
page	The HPDF page handle
t	Table handle
xpos	x position for table, bottom left corner
ypos	y position for table, bottom left corner
width	width of table
height	height of table. If the height is specified as 0 it will be automatically calculated. The calculated height can be retrieved after the table has been stroked by a call to hpdftbl get last auto height()
	can be retrieved after the table has been stroked by a call to hpuribl_get_last_auto_neight()

### Returns

-1 on error, 0 if successful

### See also

```
hpdftbl_get_last_auto_height()
hpdftbl_stroke_from_data()
```

### **Examples**

 $tut\_ex01.c$ ,  $tut\_ex02.c$ ,  $tut\_ex03.c$ ,  $tut\_ex05.c$ ,  $tut\_ex06.c$ ,  $tut\_ex07.c$ ,  $tut\_ex08.c$ ,  $tut\_ex09.c$ ,  $tut\_ex10.c$ ,  $tut\_ex11.c$ , and  $tut\_ex12.c$ .

#### 14.2.2.47 hpdftbl\_stroke\_from\_data()

Construct the table from a array specification.

Create and stroke a table specified by a data structure. This makes it easier to separate the view of the data from the model which provides the data. The intended use case is that the data structure specifies the core layout of the table together with the labels and callback functions to handle the content in each cell. Using this method to create a table also makes it much more maintainable.

#### **Parameters**

pdf_doc	The PDF overall document
pdf_page	The pageto stroke to
tbl_spec	The table specification
theme	Table theme to be applied

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_stroke()
```

### **Examples**

```
tut_ex13_1.c, and tut_ex13_2.c.
```

### 14.2.2.48 hpdftbl\_use\_header()

Enable/disable the interpretation of the top row as a header row

t	Table handle
use	TRUE to enable, FALSE to disable

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl set header style()
```

#### **Examples**

tut\_ex11.c, and tut\_ex12.c.

### 14.2.2.49 hpdftbl\_use\_labelgrid()

Set the usage of special grid style where the vertical grid only covers the label text and a gap to the next line. Horizontal lines are drawn as usual. The label grid style gives the table a "lighter" look.

#### **Parameters**

t	Table handle
use	TRUE to use label grid, FALSE o disable it

### Returns

0 on success, -1 on failure

### See also

hpdftbl\_use\_labels

### Examples

tut\_ex03.c, tut\_ex05.c, tut\_ex06.c, tut\_ex07.c, and tut\_ex08.c.

### 14.2.2.50 hpdftbl\_use\_labels()

```
int hpdftbl_use_labels (
          hpdftbl_t t,
           _Bool use )
```

Enable/Disable the use of cell labels. By default a newly created table will not use cell labels. Enabling labels will also by default enable the special label grid style. To adjust the grid style separately us the hpdftbl\_use\_labelgrid() method.

#### **Parameters**

t	Table handle	
use	Set to TRUE for cell labels	

#### Returns

0 on success, -1 on failure

See also

hpdftbl\_use\_labelgrid()

### **Examples**

tut\_ex03.c, tut\_ex05.c, tut\_ex06.c, tut\_ex07.c, and tut\_ex08.c.

## 14.3 /Users/ljp/Devel/hpdf\_table/src/hpdftbl.h File Reference

Necessary header file for HPDF table usage.

### **Data Structures**

struct text\_style

Specification of a text style.

struct border\_style

Specification for table borders.

struct hpdftbl\_cell

Specification of individual cells in the table.

struct hpdftbl

Core table handle.

• struct hpdftbl\_cell\_spec

Used in data driven table creation.

struct hpdftbl\_spec

Used in data driven table creation.

• struct hpdftbl\_theme

Define a set of styles into a table theme.

#### **Macros**

- #define HPDF\_FF\_TIMES "Times-Roman"
- #define HPDF\_FF\_TIMES\_ITALIC "Times-Italic"
- #define HPDF FF TIMES BOLD "Times-Bold"
- #define HPDF\_FF\_TIMES\_BOLDITALIC "Times-BoldItalic"
- #define HPDF FF HELVETICA "Helvetica"
- #define HPDF\_FF\_HELVETICA\_ITALIC "Helvetica-Oblique"
- #define HPDF\_FF\_HELVETICA\_BOLD "Helvetica-Bold"
- #define HPDF FF HELVETICA BOLDITALIC "Helvetica-BoldOblique"
- #define HPDF FF COURIER "Courier"
- #define HPDF FF COURIER BOLD "Courier-Bold"
- #define HPDF\_FF\_COURIER\_IALIC "Courier-Oblique"
- #define HPDF\_FF\_COURIER\_BOLDITALIC "Courier-BoldOblique"
- #define COLOR\_DARK\_RED (HPDF\_RGBColor) { 0.6f, 0.0f, 0.0f }
- #define COLOR RED (HPDF RGBColor) { 1.0f, 0.0f, 0.0f }
- #define COLOR\_LIGHT\_GREEN (HPDF\_RGBColor) { 0.9f, 1.0f, 0.9f }
- #define COLOR\_GREEN (HPDF\_RGBColor) { 0.4f, 0.9f, 0.4f }
- #define COLOR\_DARK\_GRAY (HPDF\_RGBColor) { 0.2f, 0.2f, 0.2f }
- #define COLOR\_LIGHT\_GRAY (HPDF\_RGBColor) { 0.9f, 0.9f, 0.9f }
- #define COLOR GRAY (HPDF RGBColor) { 0.5f, 0.5f, 0.5f }
- #define COLOR\_SILVER (HPDF\_RGBColor) { 0.75f, 0.75f, 0.75f }
- #define COLOR\_LIGHT\_BLUE (HPDF\_RGBColor) { 1.0f, 1.0f, 0.9f }
- #define COLOR\_BLUE (HPDF\_RGBColor) { 0.0f, 0.0f, 1.0f }
- #define COLOR\_DARK\_BLUE (HPDF\_RGBColor) { 0.0f, 0.0f, 0.6f }
- #define COLOR\_WHITE (HPDF\_RGBColor) { 1.0f, 1.0f, 1.0f }
- #define COLOR\_BLACK (HPDF\_RGBColor) { 0.0f, 0.0f, 0.0f }
- #define HPDFTBL DEFAULT TARGET ENCODING "ISO8859-4"
- #define HPDFTBL\_DEFAULT\_SOURCE\_ENCODING "UTF-8"
- #define HPDFTBL TEXT\_HALIGN\_LEFT 0
- #define HPDFTBL\_TEXT\_HALIGN\_CENTER 1
- #define HPDFTBL\_TEXT\_HALIGN\_RIGHT 2
- #define A4PAGE HEIGHT CM 29.7
- #define A4PAGE WIDTH CM 21.0
- #define A3PAGE HEIGHT CM 42.0
- #define A3PAGE\_WIDTH\_CM 29.7
- #define LETTERRPAGE HEIGHT CM 27.9
- #define LETTERRPAGE WIDTH CM 21.6
- #define LEGALPAGE HEIGHT CM 35.6
- #define LEGALPAGE\_WIDTH\_CM 21.6
- #define HPDFTBL\_END\_CELLSPECS {0, 0, 0, 0, 0, 0, 0, 0, 0}
- #define HPDF\_COLOR\_FROMRGB(r, g, b) (HPDF\_RGBColor){(r)/255.0,(g)/255.0,(b)/255.0}
- #define MIN\_CALCULATED\_PERCENT\_CELL\_WIDTH 2.0
- #define hpdftbl\_cm2dpi(c) (((HPDF\_REAL)(c))/2.54\*72)

Convert cm to dots using the default resolution (72 DPI)

### **Typedefs**

typedef enum hpdftbl\_text\_align hpdftbl\_text\_align\_t

Enumeration for horizontal text alignment.

typedef struct text\_style hpdf\_text\_style\_t

Specification of a text style.

typedef char \*(\* hpdftbl\_content\_callback\_t) (void \*, size\_t, size\_t)

Type specification for the table content callback.

typedef void(\* hpdftbl\_canvas\_callback\_t) (HPDF\_Doc, HPDF\_Page, void \*, size\_t, size\_t, HPDF\_REAL, HPDF\_REAL, HPDF\_REAL)

Type specification for the table canvas callback.

• typedef \_Bool(\* hpdftbl\_content\_style\_callback\_t) (void \*, size\_t, size\_t, char \*content, hpdf\_text\_style\_t \*)

Type specification for the content style.

typedef enum hpdftbl dash style hpdftbl line style t

Possible line dash styles in table frames.

typedef struct border style hpdf border style t

Specification for table borders.

typedef struct hpdftbl\_cell hpdftbl\_cell\_t

Type definition for the cell structure.

• typedef struct hpdftbl \* hpdftbl t

Table handle is a pointer to the hpdftbl structure.

typedef void(\* hpdftbl\_callback\_t) (hpdftbl\_t)

Callback type for optional post processing when constructing table from a data array.

• typedef struct hpdftbl cell spec hpdftbl cell spec t

Used in data driven table creation.

typedef struct hpdftbl\_spec hpdftbl\_spec\_t

Used in data driven table creation.

typedef struct hpdftbl\_theme hpdftbl\_theme\_t

Define a set of styles into a table theme.

typedef void(\* hpdftbl\_error\_handler\_t) (hpdftbl\_t, int, int, int)

TYpe for error handler function.

#### **Enumerations**

```
• enum hpdftbl_text_align { LEFT = 0 , CENTER = 1 , RIGHT = 2 }
```

Enumeration for horizontal text alignment.

```
    enum hpdftbl_dash_style {
    SOLID = 0 , DOT1 = 1 , DOT2 = 2 , DOT3 = 3 ,
    DASH1 = 4 , DASH2 = 5 , DASH3 = 6 , DASHDOT = 7 }
```

Possible line dash styles in table frames.

### **Functions**

· hpdftbl t hpdftbl create (size t rows, size t cols)

Create a new table with no title.

hpdftbl\_t hpdftbl\_create\_title (size\_t rows, size\_t cols, char \*title)

Create a new table with title top row.

• int hpdftbl\_stroke (HPDF\_Doc pdf, HPDF\_Page page, hpdftbl\_t t, HPDF\_REAL xpos, HPDF\_REAL ypos, HPDF\_REAL width, HPDF\_REAL height)

Stroke the table.

int hpdftbl\_stroke\_from\_data (HPDF\_Doc pdf\_doc, HPDF\_Page pdf\_page, hpdftbl\_spec\_t \*tbl\_spec, hpdftbl\_theme\_t \*theme)

Construct the table from a array specification.

• int hpdftbl destroy (hpdftbl t t)

Destroy a table and free all memory.

• int hpdftbl\_get\_last\_auto\_height (HPDF\_REAL \*height)

Get the height calculated for the last constructed table.

void hpdftbl set anchor top left ( Bool anchor)

Switch stroking anchor point.

\_Bool hpdftbl\_get\_anchor\_top\_left (void)

Get stroking anchor point.

hpdftbl\_error\_handler\_t hpdftbl\_set\_errhandler (hpdftbl\_error\_handler\_t)

Specify errhandler for the table routines.

const char \* hpdftbl\_get\_errstr (int err)

Translate a table error code to a human readable string.

const char \* hpdftbl\_hpdf\_get\_errstr (HPDF\_STATUS err\_code)

Function to return a human readable error string for an error code from Core HPDF library.

int hpdftbl get last errcode (const char \*\*errstr, int \*row, int \*col)

Return last error code.

void hpdftbl\_default\_table\_error\_handler (hpdftbl\_t t, int r, int c, int err)

A simple default table error handler callback that outputs the error to stderr in human readable format and quits the process.

• int hpdftbl\_apply\_theme (hpdftbl\_t t, hpdftbl\_theme\_t \*theme)

Apply a specified theme to a table.

hpdftbl\_theme\_t \* hpdftbl\_get\_default\_theme (void)

Return the default theme.

int hpdftbl\_destroy\_theme (hpdftbl\_theme\_t \*theme)

Destroy existing theme structure and free memory.

int hpdftbl\_set\_colwidth\_percent (hpdftbl\_t t, size\_t c, float w)

Set column width as percentage of overall table width.

• int hpdftbl clear spanning (hpdftbl tt)

Clear all cell spanning.

• int hpdftbl\_set\_cellspan (hpdftbl\_t t, size\_t r, size\_t c, size\_t rowspan, size\_t colspan)

Set cell spanning.

- int hpdftbl use labels (hpdftbl t t, Bool use)
- int hpdftbl\_use\_labelgrid (hpdftbl\_t t, \_Bool use)
- int hpdftbl\_set\_background (hpdftbl\_t t, HPDF\_RGBColor background)

Set table background color.

int hpdftbl\_set\_outer\_border (hpdftbl\_t t, HPDF\_REAL width, HPDF\_RGBColor color)

Specify style for table outer border.

• int hpdftbl\_set\_inner\_border (hpdftbl\_t t, HPDF\_REAL width, HPDF\_RGBColor color)

Specify style for table inner border.

• int hpdftbl\_set\_header\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_← RGBColor background)

Specify style for table heder row.

• int hpdftbl\_set\_header\_halign (hpdftbl\_t t, hpdftbl\_text\_align\_t align)

Set table header text align.

- int hpdftbl\_use\_header (hpdftbl\_t t, \_Bool use)
- int hpdftbl\_set\_label\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_← RGBColor background)

Set the font style for labels.

 int hpdftbl\_set\_row\_content\_style (hpdftbl\_t t, size\_t r, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_RGBColor background)

Set the font style for an entire row of cells.

• int hpdftbl\_set\_col\_content\_style (hpdftbl\_t t, size\_t c, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_RGBColor background)

Set the font style for an entre column of cells.

 int hpdftbl\_set\_content\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_← RGBColor background)

Set font style for text content.

 int hpdftbl\_set\_cell\_content\_style (hpdftbl\_t t, size\_t r, size\_t c, char \*font, HPDF\_REAL fsize, HPDF\_← RGBColor color, HPDF\_RGBColor background)

Set the font style for content of specified cell.

 int hpdftbl\_set\_title\_style (hpdftbl\_t t, char \*font, HPDF\_REAL fsize, HPDF\_RGBColor color, HPDF\_← RGBColor background)

Set the table title style.

• int hpdftbl\_set\_cell (hpdftbl\_t t, int r, int c, char \*label, char \*content)

Set content for specific cell.

int hpdftbl\_set\_tag (hpdftbl\_t t, void \*tag)

Set an optional tag for the table.

int hpdftbl\_set\_title (hpdftbl\_t t, char \*title)

Set table title.

int hpdftbl\_set\_title\_halign (hpdftbl\_t t, hpdftbl\_text\_align\_t align)

Set horizontal alignment for table title.

int hpdftbl\_set\_labels (hpdftbl\_t t, char \*\*labels)

Set the text for the cell labels.

int hpdftbl\_set\_content (hpdftbl\_t t, char \*\*content)

Set the content for the table.

int hpdftbl\_set\_content\_cb (hpdftbl\_t t, hpdftbl\_content\_callback\_t cb)

Set table content callback.

• int hpdftbl\_set\_cell\_content\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_content\_callback\_t cb)

Set cell content callback.

• int hpdftbl\_set\_cell\_content\_style\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_content\_style\_callback\_t cb)

Set cell specific callback to specify cell content style.

int hpdftbl\_set\_content\_style\_cb (hpdftbl\_t t, hpdftbl\_content\_style\_callback\_t cb)

Set callback to specify cell content style.

int hpdftbl\_set\_label\_cb (hpdftbl\_t t, hpdftbl\_content\_callback\_t cb)

Set table label callback.

• int hpdftbl\_set\_cell\_label\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_content\_callback\_t cb)

Set cell label callback.

• int hpdftbl\_set\_canvas\_cb (hpdftbl\_t t, hpdftbl\_canvas\_callback\_t cb)

Set cell canvas callback.

• int hpdftbl\_set\_cell\_canvas\_cb (hpdftbl\_t t, size\_t r, size\_t c, hpdftbl\_canvas\_callback\_t cb)

Set cell canvas callback.

void hpdftbl\_set\_text\_encoding (char \*target, char \*source)

Determine text source encoding.

• int hpdftbl encoding text out (HPDF Page page, HPDF REAL xpos, HPDF REAL ypos, char \*text)

Strke text with current encoding.

 void HPDF\_RoundedCornerRectangle (HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL ypos, HPDF— \_REAL width, HPDF\_REAL height, HPDF\_REAL rad)

Draw rectangle with rounded corner.

void hpdftbl stroke grid (HPDF Doc pdf, HPDF Page page)

void hpdftbl\_table\_widget\_letter\_buttons (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF\_
REAL ypos, HPDF\_REAL width, HPDF\_REAL height, HPDF\_RGBColor on\_color, HPDF\_RGBColor off\_
color, HPDF\_RGBColor on\_background, HPDF\_RGBColor off\_background, HPDF\_REAL fsize, const char \*letters, \_Bool \*state)

Display an array of letters as a table where each letter is its own "mini" cell and sorrounded by a frame. Each boxed letter can be in an "on" state or "off" state which is illustrated with different font and fac colors.

void hpdftbl\_widget\_slide\_button (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL xpos, HPDF\_REAL width, HPDF\_REAL height, \_Bool state)

Table widget that draws a sliding on/off switch. Meant to be used in a canvas callback to display a boolean value.

• void hpdftbl\_widget\_hbar (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL ypos, HPDF\_REAL width, HPDF\_REAL height, HPDF\_RGBColor color, float val, \_Bool hide\_val)

Draw a horizontal partially filled bar to indicate an analog (percentage) value.

void hpdftbl\_widget\_segment\_hbar (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL ypos, HPDF\_REAL width, HPDF\_REAL height, size\_t num\_segments, HPDF\_RGBColor on\_color, double val\_percent, \_Bool hide\_val)

Draw a horizontal segment meter that can be used to visualize a discrete value.

void hpdftbl\_widget\_strength\_meter (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL ypos, HPDF\_REAL width, HPDF\_REAL height, size\_t num\_segments, HPDF\_RGBColor on\_color, size\_t num on segments)

Draw a phone strength meter.

# 14.3.1 Detailed Description

Necessary header file for HPDF table usage.

### 14.3.2 Macro Definition Documentation

# 14.3.2.1 A3PAGE\_HEIGHT\_CM

#define A3PAGE\_HEIGHT\_CM 42.0

A3 Height in CM

## 14.3.2.2 A3PAGE\_WIDTH\_CM

#define A3PAGE\_WIDTH\_CM 29.7

A3 Width in CM

### 14.3.2.3 A4PAGE\_HEIGHT\_CM

#define A4PAGE\_HEIGHT\_CM 29.7

A4 Height in CM

### **Examples**

 $tut_ex01.c$ ,  $tut_ex02.c$ ,  $tut_ex03.c$ ,  $tut_ex05.c$ ,  $tut_ex06.c$ ,  $tut_ex07.c$ ,  $tut_ex08.c$ ,  $tut_ex09.c$ ,  $tut_ex10.c$ ,  $tut_ex11.c$ ,

## 14.3.2.4 A4PAGE\_WIDTH\_CM

```
#define A4PAGE_WIDTH_CM 21.0
```

A4 Width in CM

**Examples** 

```
tut_ex09.c, tut_ex10.c, tut_ex11.c, and tut_ex12.c.
```

### 14.3.2.5 COLOR\_DARK\_RED

```
#define COLOR_DARK_RED (HPDF_RGBColor) { 0.6f, 0.0f, 0.0f }
```

Basic color definitions

# 14.3.2.6 HPDF\_COLOR\_FROMRGB

Utility macro to calculate a color constant from RGB integer values [0,255]

## 14.3.2.7 HPDF\_FF\_TIMES

```
#define HPDF_FF_TIMES "Times-Roman"
```

Definition of built-in HPDF font families

**Examples** 

tut ex09.c.

# 14.3.2.8 hpdftbl\_cm2dpi

Convert cm to dots using the default resolution (72 DPI)

**Parameters** 

cm Measure in cm

Returns

HPDF\_REAL Converted value in dots

### **Examples**

 $tut\_ex01.c$ ,  $tut\_ex02.c$ ,  $tut\_ex03.c$ ,  $tut\_ex05.c$ ,  $tut\_ex06.c$ ,  $tut\_ex07.c$ ,  $tut\_ex08.c$ ,  $tut\_ex09.c$ ,  $tut\_ex10.c$ ,  $tut\_ex11.c$ ,  $tut\_ex12.c$ ,  $tut\_ex13\_1.c$ , and  $tut\_ex13\_2.c$ .

### 14.3.2.9 HPDFTBL\_DEFAULT\_TARGET\_ENCODING

#define HPDFTBL\_DEFAULT\_TARGET\_ENCODING "ISO8859-4"

Text encodings

# 14.3.2.10 HPDFTBL\_END\_CELLSPECS

#define HPDFTBL\_END\_CELLSPECS {0, 0, 0, 0, 0, 0, 0, 0}

Sentinel to mark the end of Cell Specifications for data driven table definition

# **Examples**

tut\_ex13\_2.c.

## 14.3.2.11 LEGALPAGE\_HEIGHT\_CM

#define LEGALPAGE\_HEIGHT\_CM 35.6

US Legal Height in CM

## 14.3.2.12 LEGALPAGE\_WIDTH\_CM

#define LEGALPAGE\_WIDTH\_CM 21.6

US Legal Width in CM

# 14.3.2.13 LETTERRPAGE\_HEIGHT\_CM

#define LETTERRPAGE\_HEIGHT\_CM 27.9

US Letter Height in CM

## 14.3.2.14 LETTERRPAGE\_WIDTH\_CM

```
#define LETTERRPAGE_WIDTH_CM 21.6
```

US Letter Width in CM

## 14.3.2.15 MIN\_CALCULATED\_PERCENT\_CELL\_WIDTH

```
#define MIN_CALCULATED_PERCENT_CELL_WIDTH 2.0
```

The smallest size in percent of table width allowed by automatic calculation before giving an error

# 14.3.3 Typedef Documentation

## 14.3.3.1 hpdf border style t

```
typedef struct border_style hpdf_border_style_t
```

Specification for table borders.

Contains line properties used when stroking a border line

## 14.3.3.2 hpdf\_text\_style\_t

```
typedef struct text_style hpdf_text_style_t
```

Specification of a text style.

This structure collects the basic properties for a text string (font, color, background, horizontal alignment)

### 14.3.3.3 hpdftbl\_callback\_t

```
typedef void(* hpdftbl_callback_t) (hpdftbl_t)
```

Callback type for optional post processing when constructing table from a data array.

Type for generic table callback used when constructing a table from data. This can be used to perform any potential table manipulation. The callback happens after the table has been fully constructed and just before it is stroked.

See also

hpdftbl stroke from data()

### 14.3.3.4 hpdftbl\_canvas\_callback\_t

```
typedef void(* hpdftbl_canvas_callback_t) (HPDF_Doc, HPDF_Page, void *, size_t, size_t, HPDF_\leftrightarrow REAL, HPDF_REAL, HPDF_REAL, HPDF_REAL)
```

Type specification for the table canvas callback.

A canvas callback, if specified, is called for each cell before the content is stroked. The callback will be given the bounding box for the cell (x,y,width,height) in addition to the row and column the cell has.

See also

hpdftbl\_set\_canvas\_callback()

### 14.3.3.5 hpdftbl\_cell\_spec\_t

```
typedef struct hpdftbl_cell_spec hpdftbl_cell_spec_t
```

Used in data driven table creation.

A table can be specified by creating a array of this structure together with the hpdftbl\_spec\_t structure. The array should have one entry for each cell in the table.

See also

hpdftbl\_stroke\_from\_data()

## 14.3.3.6 hpdftbl\_cell\_t

```
typedef struct hpdftbl_cell hpdftbl_cell_t
```

Type definition for the cell structure.

This is an internal structure that represents an individual cell in the table.

## 14.3.3.7 hpdftbl\_content\_callback\_t

```
typedef char *(* hpdftbl_content_callback_t) (void *, size_t, size_t)
```

Type specification for the table content callback.

The content callback is used to specify the textual content in a cell and is an alternative method to specifying the content to be displayed.

See also

hpdftbl\_set\_content\_callback()

### 14.3.3.8 hpdftbl\_content\_style\_callback\_t

```
typedef _Bool(* hpdftbl_content_style_callback_t) (void *, size_t, size_t, char *content, hpdf_text_style_t
*)
```

Type specification for the content style.

The content callback is used to specify the textual style in a cell and is an alternative method to specifying the style of content to be displayed.

See also

```
hpdftbl set content style callback()
```

## 14.3.3.9 hpdftbl\_error\_handler\_t

```
typedef void(* hpdftbl_error_handler_t) (hpdftbl_t, int, int, int)
```

TYpe for error handler function.

The error handler (of set) will be called if the table library descovers an error condition

See also

hpdftbl\_set\_errhandler()

## 14.3.3.10 hpdftbl\_spec\_t

```
typedef struct hpdftbl_spec hpdftbl_spec_t
```

Used in data driven table creation.

This is used together with an array of cell specification hpdftbl\_cell\_spec\_t to specify the layout of a table.

### 14.3.3.11 hpdftbl\_t

```
typedef struct hpdftbl* hpdftbl_t
```

Table handle is a pointer to the hpdftbl structure.

This is the basic table handle used in almost all API calls. A table reference is returned when a table is created.

See also

hpdftbl\_create()

## 14.3.3.12 hpdftbl\_text\_align\_t

```
typedef enum hpdftbl_text_align hpdftbl_text_align_t
```

Enumeration for horizontal text alignment.

### See also

```
hpdftbl_set_header_halign()
hpdftbl_set_title_halign()
hpdftbl_text_align
```

## 14.3.3.13 hpdftbl\_theme\_t

```
typedef struct hpdftbl_theme hpdftbl_theme_t
```

Define a set of styles into a table theme.

Contains all information about the styles of various elements in the table that together make up the table style

# 14.3.4 Enumeration Type Documentation

# 14.3.4.1 hpdftbl\_dash\_style

```
enum hpdftbl_dash_style
```

Possible line dash styles in table frames.

### Enumerator

SOLID	Solid line
DOT1	Dotted line variant 1
DOT2	Dotted line variant 2
DOT3	Dotted line variant 3
DASH1	Dashed line variant 1
DASH2	Dashed line variant 2
DASH3	Dashed line variant 3
DASHDOT	Dashed-dot line variant 1

# 14.3.4.2 hpdftbl\_text\_align

```
\verb"enum hpdftbl_text_align"
```

Enumeration for horizontal text alignment.

### See also

```
hpdftbl_set_header_halign()
hpdftbl_set_title_halign()
hpdftbl_text_align
```

#### Enumerator

LEFT	Left test alignment
CENTER	Center test alignment
RIGHT	Right test alignment

# 14.3.5 Function Documentation

# 14.3.5.1 HPDF\_RoundedCornerRectangle()

Draw rectangle with rounded corner.

Draw a rectangle with rounded corner with the current line width, color. The rectangle will not be stroked.

### **Parameters**

page	Page handle	
xpos	Lower left x-position of rectangle	
ypos	Lower left y-position of rectangle	
width	Width of rectangle	
height	Height of rectangle	
rad	Radius of corners	

Referenced by hpdftbl\_widget\_slide\_button().

## 14.3.5.2 hpdftbl\_apply\_theme()

```
int hpdftbl_apply_theme (
```

```
hpdftbl_t t,
hpdftbl_theme_t * theme )
```

Apply a specified theme to a table.

Apply a specified theme to a table. The default table can be retrieved with hpdftbl\_get\_default\_theme()

#### **Parameters**

t	Table handle	
theme	Theme reference	

# Returns

0 on success, -1 on failure

### See also

hpdftbl\_get\_default\_theme()

## 14.3.5.3 hpdftbl\_clear\_spanning()

```
int hpdftbl_clear_spanning ( \label{eq:hpdftbl_t} \operatorname{hpdftbl_t} t \ t \ )
```

Clear all cell spanning.

Reset all spanning cells to no spanning

### **Parameters**

```
t Table handle
```

### Returns

0 on success, -1 on failure

See also

hpdftbl\_set\_cellspan()

# 14.3.5.4 hpdftbl\_create()

Create a new table with no title.

Create a new table structure. This is the basic handler needed for most other API functions.

### **Parameters**

rows	Number of rows
cols	Number of columns

### Returns

A handle to a table, NULL in case of OOM

# 14.3.5.5 hpdftbl\_create\_title()

Create a new table with title top row.

Create a new table structure. This is the basic handler needed for most other API functions.

#### **Parameters**

rows	Number of rows
cols	Number of columns
title	Title of table

### Returns

A handle to a table, NULL in case of OOM

Referenced by hpdftbl\_create(), and hpdftbl\_stroke\_from\_data().

# 14.3.5.6 hpdftbl\_default\_table\_error\_handler()

A simple default table error handler callback that outputs the error to stderr in human readable format and quits the process.

# Parameters

t	Table where the error happened (can be NULL)
r	Cell row
С	Cell column
err	The error code

### 14.3.5.7 hpdftbl destroy()

```
int hpdftbl_destroy ( \begin{array}{c} \text{hpdftbl\_t } t \end{array})
```

Destroy a table and free all memory.

Destroy a table previous created with table\_create()

#### **Parameters**

```
t Handle to table
```

#### Returns

0 on success, -1 on failure

## 14.3.5.8 hpdftbl\_destroy\_theme()

Destroy existing theme structure and free memory.

Free all memory allocated by a theme

#### **Parameters**

```
theme The theme to free
```

# 14.3.5.9 hpdftbl\_encoding\_text\_out()

Strke text with current encoding.

Utility function to stroke text with character encoding. It is the calling routines responsibility to enclose text in a  $HPDF\_Page\_BeginText() / HPDF\_Page\_EndText()$ 

#### **Parameters**

page	Page handle
xpos	X coordinate
ypos	Y coordinate
text	Text to print

### Returns

-1 on error, 0 on success

## 14.3.5.10 hpdftbl\_get\_anchor\_top\_left()

```
_Bool hpdftbl_get_anchor_top_left ( void )
```

Get stroking anchor point.

Get base point for table positioning. By default the top left is used.

See also

hpdftbl\_set\_anchor\_top\_left

## 14.3.5.11 hpdftbl\_get\_default\_theme()

Return the default theme.

Create and return a theme corresponding to the default table theme. It is the calling functions responsibility to call <a href="hpdftbl\_destroy\_theme">hpdftbl\_destroy\_theme</a>() to free the allocated memory. The default theme is a good starting point to just make minor modifications without having to define all elements.

Returns

A new theme initialized to the default settings

See also

hpdftbl\_apply\_theme()

### 14.3.5.12 hpdftbl\_get\_errstr()

Translate a table error code to a human readable string.

The function returns a pointer to a static string that cannot be modified. It will translate both internal table error messages as well as generic HPDF library error codes.

### **Parameters**

err_code	The error code to be translated
----------	---------------------------------

## Returns

Static pointer to string for valid error code, NULL otherwise

#### See also

```
hpdftbl_hpdf_get_errstr()
```

Referenced by hpdftbl default table error handler(), and hpdftbl get last errcode().

## 14.3.5.13 hpdftbl\_get\_last\_auto\_height()

```
int hpdftbl_get_last_auto_height ( \label{eq:hpdf} \texttt{HPDF\_REAL} \ * \ height \ )
```

Get the height calculated for the last constructed table.

Get the last automatically calculated heigh when stroking a table. (The height will be automatically calculated if it was specified as 0)

### **Parameters**

```
height Returned height
```

### Returns

-1 on error, 0 if successful

## 14.3.5.14 hpdftbl\_get\_last\_errcode()

Return last error code.

Return last error code. if errstr is not NULL a human readable string describing the error will be copied to the string. The error code will be reset after call.

#### **Parameters**

errstr	A string buffer where the error string is written to	
row	The row where the error was found	
col	The col where the error was found	

#### Returns

The last error code

## 14.3.5.15 hpdftbl\_hpdf\_get\_errstr()

Function to return a human readable error string for an error code from Core HPDF library.

The various error codes given by the HPDF library can be translated back to a string by the usage of this function. The function will return a pointer to a static string that can not be manipulated.

#### **Parameters**

err_code	The error code
----------	----------------

### Returns

A pointer to an error string, NULL if the error code is invalid

### See also

```
hpdftbl_get_errstr()
```

## **Examples**

tut\_ex01.c, tut\_ex02.c, tut\_ex03.c, tut\_ex05.c, tut\_ex06.c, tut\_ex07.c, tut\_ex08.c, tut\_ex09.c, tut\_ex10.c, tut\_ex11.c, tut\_ex12.c, tut\_ex13\_1.c, and tut\_ex13\_2.c.

### 14.3.5.16 hpdftbl\_set\_anchor\_top\_left()

Switch stroking anchor point.

Set anchor point for table positioning. By default the top left is used as anchor. Calling this function with FALSE can set the basepoint to bottom left instead.

#### **Parameters**

anchor	Set to TRUE to use top left as anchor, FALSE for bottom left
--------	--

## 14.3.5.17 hpdftbl\_set\_background()

Set table background color.

Set table background

### **Parameters**

t	Table handle
background	Background color

#### Returns

0 on success, -1 on failure

# 14.3.5.18 hpdftbl\_set\_canvas\_cb()

Set cell canvas callback.

Set cell canvas callback. This callback gets called for each cell in the table. The purpose is to allow the client to add dynamic content to the specified cell. The callback is made before the cell border and content is drawn making it possible to for example add a background color to individual cells. The callback function will receive the Table tag, the row and column, the x, y position of the lower left corner of the table and the width and height of the cell. To set the canvas callback only for a sepcific cell use the hpdftbl\_set\_cell\_canvas\_callback() function

#### **Parameters**

t	Table handle
cb	Callback function

#### Returns

-1 on failure, 0 otherwise

#### See also

```
hpdftbl_set_cell_canvas_cb()
```

## 14.3.5.19 hpdftbl\_set\_cell()

```
int hpdftbl_set_cell (
    hpdftbl_t t,
    int r,
    int c,
    char * label,
    char * content )
```

Set content for specific cell.

Set label and content for a specific cell. If the specified cell is part of another cells spanning then error is given (returns -1),

#### **Parameters**

t	Table handle
r	Row
С	Column
label	Label
content	Text content

## Returns

-1 on error, 0 if successful

## 14.3.5.20 hpdftbl\_set\_cell\_canvas\_cb()

Set cell canvas callback.

Set a canvas callback for an individual cell. This will override the table canvas callback. The canvas callback is called with arguments that give the bounding box for the cell. In that way a callback function may draw arbitrary graphic in the cell. The callback is made before the cell border and content is drawn making it possible to for example add a background color to individual cells. The callback function will receive the Table tag, the row and column, the x, y position of the lower left corner of the table and the width and height of the cell.

### **Parameters**

t	Table handle	
r	Cell row	
С	Cell column	
cb	Callback function	

## Returns

-1 on failure, 0 otherwise

### See also

```
hpdftbl_canvas_callback_t
hpdftbl_set_canvas_callback
```

# 14.3.5.21 hpdftbl\_set\_cell\_content\_cb()

```
int hpdftbl_set_cell_content_cb (
          hpdftbl_t t,
          size_t r,
          size_t c,
          hpdftbl_content_callback_t cb )
```

Set cell content callback.

Set a content callback for an individual cell. This will override the table content callback.

## **Parameters**

t	Table handle	
cb	Callback function	
r	Cell row	
С	Cell column	

# Returns

-1 on failure, 0 otherwise

### See also

```
hpdftbl_set_content_cb()
```

### 14.3.5.22 hpdftbl\_set\_cell\_content\_style()

```
int hpdftbl_set_cell_content_style (
    hpdftbl_t t,
    size_t r,
    size_t c,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set the font style for content of specified cell.

SSet the font style for content of specified cell. This will override the global cell content setting.

#### **Parameters**

t	Table handle
r	Cell row
С	Cell column
font	Font name
fsize	Font size
color	Color
background	Background color

### Returns

0 on success, -1 on failure

### See also

```
hpdftbl_set_content_style()
hpdftbl_set_cell_content_style_cb()
```

Referenced by hpdftbl\_set\_col\_content\_style(), and hpdftbl\_set\_row\_content\_style().

# 14.3.5.23 hpdftbl\_set\_cell\_content\_style\_cb()

Set cell specific callback to specify cell content style.

Set callback to format the style for the specified cell

### **Parameters**

t	Table handle
r	Cell row
С	Cell column
cb	Callback function

## Returns

0 on success, -1 on failure

### See also

hpdftbl\_set\_ontent\_style\_cb()

# 14.3.5.24 hpdftbl\_set\_cell\_label\_cb()

```
int hpdftbl_set_cell_label_cb (
          hpdftbl_t t,
          size_t r,
          size_t c,
          hpdftbl_content_callback_t cb )
```

Set cell label callback.

Set a label callback for an individual cell. This will override the table content callback.

### **Parameters**

t	Table handle	
cb	Callback function	
r	Cell row	
С	Cell column	

# Returns

-1 on failure, 0 otherwise

# See also

hpdftbl\_set\_label\_cb()

## 14.3.5.25 hpdftbl\_set\_cellspan()

```
int hpdftbl_set_cellspan (
          hpdftbl_t t,
          size_t r,
          size_t c,
          size_t rowspan,
          size_t colspan )
```

Set cell spanning.

Set row and column spanning for a cell

#### **Parameters**

t	Table handle
r	Row
С	Column
rowspan	Row span
colspan	Column span

#### Returns

-1 on error, 0 if successful

## See also

hpdftbl\_clear\_spanning()

# 14.3.5.26 hpdftbl\_set\_col\_content\_style()

Set the font style for an entre column of cells.

Set font options for the specified column of cells. This will override the global cell content setting.

## Parameters

t	Table handle
С	Column to affect
font	Font name
fsize	Font size
color	Color
background	Background color

#### Returns

0 on success, -1 on failure

#### See also

```
hpdftbl_set_content_style()
hpdftbl_set_cell_content_style_cb()
```

## 14.3.5.27 hpdftbl\_set\_colwidth\_percent()

```
int hpdftbl_set_colwidth_percent (
          hpdftbl_t t,
          size_t c,
          float w )
```

Set column width as percentage of overall table width.

Specify column width as percentage of total column width. Note that this will only take effect if the table has an overall width specified when stroked.

#### **Parameters**

t	Table handle	
С	Column to set width of first column has index 0	
W	Width as percentage in range [0.0, 100.0]	

### Returns

0 on success, -1 on failure

### 14.3.5.28 hpdftbl\_set\_content()

Set the content for the table.

Set content for all cells. It is the calling functions responsibility that the content array is big enough to cover the entire table. The string array corresponds to a flattened 2-d array and the label for cell (r,c) is calculated as  $(r*num\_cols+c)$  where num\\_cols is the number of columns in the table. It is allowed to specify NULL as placeholder for empty labels. The actual text in the table will be allocated with strdup() so it is safe to free the memory for the labels after the call to this function. Please note that even if the table contains spanning cells the content data must include empty data for covered cells. For a N x M table the data must have (N\*M) entries. Another way to specify the content is to use the callback mechanism. By setting up a content callback function that returns the content for a cell

#### **Parameters**

t	Table handle
content	A one dimensional string array of content string

### Returns

-1 on error, 0 if successful

## See also

```
hpdftbl_set_content_callback()
hpdftbl_set_cell_content_callback()
```

## 14.3.5.29 hpdftbl\_set\_content\_cb()

Set table content callback.

Set content callback. This callback gets called for each cell in the table and the returned string will be used as the content. The string will be duplicated so it is safe for a client to reuse the string space. If NULL is returned from the callback then the content will be set to the content specified with the direct content setting. The callback function will receive the Table tag and the row and column

#### **Parameters**

t	Table handle	
cb	Callback function	

### See also

```
hpdftbl_set_cell_content_cb()
```

# 14.3.5.30 hpdftbl\_set\_content\_style()

```
int hpdftbl_set_content_style (
    hpdftbl_t t,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set font style for text content.

Set font options for cell content. This will be applied for all cells in the table.

#### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Color
background	Background color

## Returns

-1 on error, 0 if successful

### See also

```
hpdftbl_set_cell_content_style()
hpdftbl_set_cell_content_style_cb()
```

## 14.3.5.31 hpdftbl\_set\_content\_style\_cb()

Set callback to specify cell content style.

Set callback to format the style for cells in the table. If a cell has its own content style callback that callback will override the generic table callback.

#### **Parameters**

t	Table handle	
cb	Callback function	

## Returns

0 on success, -1 on failure

### See also

hpdftbl\_set\_cell\_content\_style\_cb()

### 14.3.5.32 hpdftbl\_set\_errhandler()

Specify errhandler for the table routines.

### **Parameters**

```
err_handler
```

## Returns

The old error handler or NULL if non exists

## 14.3.5.33 hpdftbl\_set\_header\_halign()

Set table header text align.

Set horizontal text alignment for header row

#### **Parameters**

t	Table handle
align	Alignment

# Returns

0 on success, -1 on failure

## 14.3.5.34 hpdftbl\_set\_header\_style()

```
int hpdftbl_set_header_style (
          hpdftbl_t t,
          char * font,
          HPDF_REAL fsize,
          HPDF_RGBColor color,
          HPDF_RGBColor background )
```

Specify style for table heder row.

Set the font properties and background for the header row which is the top row if enabled. The header row will be automatically enabled after calling this function. The header can be enabled/disabled separately with hpdftbl\_use\_header()

### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Font color
background	Cell background color

#### Returns

0 on success, -1 on failure hpdftbl\_use\_header()

## 14.3.5.35 hpdftbl\_set\_inner\_border()

Specify style for table inner border.

Set inner border properties

#### **Parameters**

t	Table handle
width	Line width
color	Line color

#### Returns

0 on success, -1 on failure

## 14.3.5.36 hpdftbl\_set\_label\_cb()

```
int hpdftbl_set_label_cb ( \label{eq:hpdftbl_t} \mbox{hpdftbl_t} \ t \mbox{,} \\ \mbox{hpdftbl\_content\_callback\_t} \ cb \ )
```

Set table label callback.

Set label callback. This callback gets called for each cell in the table and the returned string will be used as the label. The string will be duplicated so it is safe for a client to reuse the string space. If NULL is returned from the callback then the label will be set to the content specified with the direct label setting. The callback function will receive the Table tag and the row and column

### **Parameters**

t	Table handle	
cb	cb Callback function	

## Returns

-1 on failure, 0 otherwise

#### See also

```
hpdftbl_content_callback_t
hpdftbl_set_cell_label_cb()
```

# 14.3.5.37 hpdftbl\_set\_label\_style()

Set the font style for labels.

Set font, color and background options for cell labels.

#### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Color
background	Background color

### Returns

-1 on error, 0 if successful

## 14.3.5.38 hpdftbl\_set\_labels()

Set the text for the cell labels.

Set labels for all the cell. It is the calling functions responsibility that the labels array is big enough to cover the entire table. The string array corresponds to a flattened 2-d array and the label for cell (r,c) is calculated as  $(r * num\_cols + c)$  where  $num\_cols$  is the number of columns in the table. It is allowed to specify NULL as placeholder for empty labels. The actual text in the table will be allocated with strdup() so it is safe to free the memory for the labels after the call to this function. Please note that even if the table contains spanning cells the content data must include empty data for covered cells. For a N x M table the data must have (N\*M) entries.

### **Parameters**

t	Table handle	
labels	els A one dimensional string array of labels	

### Returns

-1 on error, 0 if successful

## See also

```
hpdftbl_set_cell_label_cb()
hpdftbl_set_label_cb()
```

## 14.3.5.39 hpdftbl\_set\_outer\_border()

Specify style for table outer border.

Set outer border properties

#### **Parameters**

t	Table handle
width	Line width
color	Line color

## Returns

0 on success, -1 on failure

### 14.3.5.40 hpdftbl\_set\_row\_content\_style()

```
int hpdftbl_set_row_content_style (
    hpdftbl_t t,
    size_t r,
    char * font,
    HPDF_REAL fsize,
    HPDF_RGBColor color,
    HPDF_RGBColor background )
```

Set the font style for an entire row of cells.

Set font options for the specified row of cells. This will override the global cell content .

# **Parameters**

t	Table handle
---	--------------

#### **Parameters**

r	Row to affect
font	Font name
fsize	Font size
color	Color
background	Background color

### Returns

0 on success, -1 on failure

### See also

```
hpdftbl_set_content_style()
hpdftbl_set_cell_content_style_cb()
```

## 14.3.5.41 hpdftbl\_set\_tag()

```
int hpdftbl_set_tag ( \begin{array}{c} & \text{hpdftbl\_t } t \text{,} \\ & \text{void} * tag \end{array})
```

Set an optional tag for the table.

Set an optional tag in the table. The tag can be a pointer to anything. The tag is passed as the first argument in the various callbacks and can be used to supply table specific information or identify a specific table in the case the same callback is used for multiple tables.

## **Parameters**

t	The table handle
tag	The tag (pointer to any object)

### Returns

0 on success, -1 on failure

# 14.3.5.42 hpdftbl\_set\_text\_encoding()

Determine text source encoding.

The default HPDF encoding is a standard PDF encoding. The problem with that is that now almost 100% of all code is written in UTF-8 encoding and trying to print text strings with accented charactes will simply not work. For example the default encoding assumes that strings are given in UTF-8 and sets the target to ISO8859-4 which includes northern europe accented characters. The conversion is internally handled by the standard iconv() routines.

### **Parameters**

target	The target encoding. See HPDF documentation for supported encodings.
source	The source encodings, i.e. what encodings are sth strings in the source specified in.

## 14.3.5.43 hpdftbl\_set\_title()

```
int hpdftbl_set_title (
          hpdftbl_t t,
           char * title )
```

Set table title.

Set table title

#### **Parameters**

t	Table handle
title	Title string

### Returns

0 on success, -1 on failure

## See also

```
hpdftbl_set_title_style()
hpdftbl_set_title_halign()
```

## 14.3.5.44 hpdftbl\_set\_title\_halign()

Set horizontal alignment for table title.

Set horizontal text alignment for title

## **Parameters**

t	Table handle
align	Alignment

# Returns

0 on success, -1 on failure

## See also

```
hpdftbl_set_title()
hpdftbl_set_title_style()
```

# 14.3.5.45 hpdftbl\_set\_title\_style()

```
int hpdftbl_set_title_style (
          hpdftbl_t t,
          char * font,
          HPDF_REAL fsize,
          HPDF_RGBColor color,
          HPDF_RGBColor background )
```

Set the table title style.

Set font options for title

### **Parameters**

t	Table handle
font	Font name
fsize	Font size
color	Color
background	Background color

## Returns

0 on success, -1 on failure

### See also

```
hpdftbl_set_title()
hpdftbl_set_title_halign()
```

### 14.3.5.46 hpdftbl\_stroke()

Stroke the table.

Stroke the table at the specified position and size. The position is by default specified as the upper left corner of the table. Use the hpdftbl\_set\_origin\_top\_left(FALSE) to use the bottom left of the table as reference point.

### **Parameters**

pdf	The HPDF document handle
page	The HPDF page handle
t	Table handle
xpos	x position for table, bottom left corner
ypos	y position for table, bottom left corner
width	width of table
height	height of table. If the height is specified as 0 it will be automatically calculated. The calculated height can be retrieved after the table has been stroked by a call to hpdftbl_get_last_auto_height()

#### Returns

-1 on error, 0 if successful

### See also

```
hpdftbl_get_last_auto_height()
hpdftbl_stroke_from_data()
```

## 14.3.5.47 hpdftbl\_stroke\_from\_data()

Construct the table from a array specification.

Create and stroke a table specified by a data structure. This makes it easier to separate the view of the data from the model which provides the data. The intended use case is that the data structure specifies the core layout of the table together with the labels and callback functions to handle the content in each cell. Using this method to create a table also makes it much more maintainable.

### **Parameters**

pdf_doc	The PDF overall document
pdf_page	The pageto stroke to
tbl_spec	The table specification
theme	Table theme to be applied

## Returns

0 on success, -1 on failure

### See also

hpdftbl stroke()

## 14.3.5.48 hpdftbl\_stroke\_grid()

Stroke a point grid on specified page to make it easier to position text and tables.

### **Parameters**

pdf	Document handle
page	Page handle

## **Examples**

 $tut\_ex01.c$ ,  $tut\_ex02.c$ ,  $tut\_ex03.c$ ,  $tut\_ex05.c$ ,  $tut\_ex06.c$ ,  $tut\_ex07.c$ ,  $tut\_ex08.c$ ,  $tut\_ex09.c$ ,  $tut\_ex10.c$ ,  $tut\_ex11.c$ ,  $tut\_ex12.c$ ,  $tut\_ex13\_1.c$ , and  $tut\_ex13\_2.c$ .

# 14.3.5.49 hpdftbl\_table\_widget\_letter\_buttons()

```
const HPDF_RGBColor on_background,
const HPDF_RGBColor off_background,
const HPDF_REAL fsize,
const char * letters,
_Bool * state )
```

Display an array of letters as a table where each letter is its own "mini" cell and sorrounded by a frame. Each boxed letter can be in an "on" state or "off" state which is illustrated with different font and fac colors.

### **Parameters**

doc	HPDF document handle
page	HPDF page handle
xpos	X-öosition of cell
ypos	Y-Position of cell
width	Width of cell
height	Height of cell
on_color	The font color in "on" state
off_color	The font color in "off" state
on_background	The face color in "on" state
off_background	The face color in "off" state
fsize	The font size
letters	What letters to have in the boxes
state	What state each boxed letter should be (0=off, 1=pn)

# 14.3.5.50 hpdftbl\_use\_header()

Enable/disable the interpretation of the top row as a header row

#### **Parameters**

t	Table handle
use	TRUE to enable, FALSE to disable

# Returns

0 on success, -1 on failure

## See also

hpdftbl\_set\_header\_style()

## 14.3.5.51 hpdftbl\_use\_labelgrid()

Set the usage of special grid style where the vertical grid only covers the label text and a gap to the next line. Horizontal lines are drawn as usual. The label grid style gives the table a "lighter" look.

#### **Parameters**

t	Table handle
use	TRUE to use label grid, FALSE o disable it

### Returns

0 on success, -1 on failure

#### See also

hpdftbl\_use\_labels

# 14.3.5.52 hpdftbl\_use\_labels()

Enable/Disable the use of cell labels. By default a newly created table will not use cell labels. Enabling labels will also by default enable the special label grid style. To adjust the grid style separately us the hpdftbl\_use\_labelgrid() method.

### **Parameters**

t	Table handle
use	Set to TRUE for cell labels

## Returns

0 on success, -1 on failure

### See also

hpdftbl\_use\_labelgrid()

#### 14.3.5.53 hpdftbl\_widget\_hbar()

Draw a horizontal partially filled bar to indicate an analog (percentage) value.

This function can not be used directly as a canvas callback since it needs additional parameters. Instead create a simple canvas callback that gives the additional parameters.

#### **Parameters**

doc	HPDF Document handle
page	HPDF Page handle
xpos	Lower left x
ypos	Lower left y
width	Width of meter
height	Height of meter
color	Fill color for bar
val	Percentage fill in range [0.0, 100.0]
show_val	TRUE to show the value (in percent) at the right end of the entire bar

## 14.3.5.54 hpdftbl\_widget\_segment\_hbar()

Draw a horizontal segment meter that can be used to visualize a discrete value.

This function can not be used directly as a canvas callback since it needs additional parameters. Instead create a simple canvas callback that gives the additional parameters.

134 File Documentation

#### **Parameters**

doc	HPDF Document handle
page	HPDF Page handle
xpos	Lower left x
ypos	Lower left y
width	Width of meter
height	Height of meter
num_segments	Total number of segments
on_color	Color for "on" segment
num_on_segments	Number of on segments

## 14.3.5.55 hpdftbl\_widget\_slide\_button()

Table widget that draws a sliding on/off switch. Meant to be used in a canvas callback to display a boolean value.

This function can not be used directly as a canvas callback since it needs the state of the button as an argument. Instead create a simple canvas callback that determines the wanted state and then just passes on all argument to this widget function.

## Parameters

doc	HPDF document handle
page	HPDF page handle
xpos	X-öosition of cell
ypos	Y-Position of cell
width	Width of cell
height	Height of cell
state	State of button On/Off

# 14.3.5.56 hpdftbl\_widget\_strength\_meter()

14.4 hpdftbl.h 135

```
const HPDF_REAL ypos,
const HPDF_REAL width,
const HPDF_REAL height,
const size_t num_segments,
const HPDF_RGBColor on_color,
const size_t num_on_segments)
```

#### Draw a phone strength meter.

This function can not be used directly as a canvas callback since it needs additional parameters. Instead create a simple canvas callback that gives the additional parameters.

#### **Parameters**

doc	HPDF Document handle
page	HPDF Page handle
xpos	Lower left x
ypos	Lower left y
width	Width of meter
height	Height of meter
num_segments	Total number of segments
on_color	Color for "on" segment
num_on_segments	Number of on segments

# 14.4 hpdftbl.h

#### Go to the documentation of this file.

```
\star Description: Utility module for flexible table drawing with HPDF library
                    Johan Persson (johan162@gmail.com)
   * Copyright (C) 2022 Johan Persson
   * Released under the MIT License
10 \, \star Permission is hereby granted, free of charge, to any person obtaining a copy
   * of this software and associated documentation files (the "Software"), to deal * in the Software without restriction, including without limitation the rights
11
12
   * to use, copy, modify, merge, publish, distribute, sublicense, and/or sell * copies of the Software, and to permit persons to whom the Software is
13
    * furnished to do so, subject to the following conditions:
16
17
    \star The above copyright notice and this permission notice shall be included in all
18
    \star copies or substantial portions of the Software.
19
   * THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR
    * IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,
   * FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE
   * AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER * LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
2.3
24
   * OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE
25
   * SOFTWARE.
26
28 */
29
37 #ifndef hpdftbl_H
38 #define
               hpdftbl_H
               __cplusplus
41 // in case we have C++ code, we should use its' types and logic
42 #include <algorithm>
43 typedef std::_Bool _Bool;
44 #endif
45
46 #ifdef
             __cplusplus
```

136 File Documentation

```
47 extern "C" {
48 #endif
49
53 #define HPDF_FF_TIMES "Times-Roman"
54 #define HPDF_FF_TIMES_ITALIC "Times-Italic"
55 #define HPDF_FF_TIMES_BOLD "Times-Bold"
56 #define HPDF_FF_TIMES_BOLDITALIC "Times-BoldItalic"
58 #define HPDF_FF_HELVETICA "Helvetica"
59 #define HPDF_FF_HELVETICA_ITALIC "Helvetica-Oblique"
60 #define HPDF_FF_HELVETICA_BOLD "Helvetica-Bold"
61 #define HPDF_FF_HELVETICA_BOLDITALIC "Helvetica-BoldOblique"
63 #define HPDF_FF_COURIER "Courier"
64 #define HPDF_FF_COURIER_BOLD "Courier-Bold"
65 #define HPDF_FF_COURIER_IALIC "Courier-Oblique"
66 #define HPDF_FF_COURIER_BOLDITALIC "Courier-BoldOblique"
67
71 #define COLOR_DARK_RED
                                   (HPDF_RGBColor) { 0.6f, 0.0f, 0.0f
72 #define COLOR_RED
                                   (HPDF_RGBColor) { 1.0f, 0.0f, 0.0f
73 #define COLOR_LIGHT_GREEN
                                   (HPDF_RGBColor) { 0.9f, 1.0f, 0.9f
74 #define COLOR_GREEN
                                   (HPDF_RGBColor) { 0.4f, 0.9f, 0.4f
75 #define COLOR_DARK_GRAY
                                   (HPDF_RGBColor) { 0.2f, 0.2f, 0.2f
76 #define COLOR_LIGHT_GRAY
                                   (HPDF_RGBColor) { 0.9f, 0.9f, 0.9f
(HPDF_RGBColor) { 0.5f, 0.5f, 0.5f
77 #define COLOR_GRAY
78 #define COLOR_SILVER
                                   (HPDF_RGBColor) { 0.75f, 0.75f, 0.75f
79 #define COLOR_LIGHT_BLUE
                                   (HPDF_RGBColor) { 1.0f, 1.0f, 0.9f
80 #define COLOR_BLUE
                                   (HPDF_RGBColor) { 0.0f, 0.0f, 1.0f
                                  (HPDF_RGBColor) { 0.0f, 0.0f, 0.6f
(HPDF_RGBColor) { 1.0f, 1.0f, 1.0f
81 #define COLOR_DARK_BLUE
82 #define COLOR_WHITE
83 #define COLOR BLACK
                                   (HPDF RGBColor) { 0.0f, 0.0f, 0.0f
88 #define HPDFTBL_DEFAULT_TARGET_ENCODING "ISO8859-4"
89 #define HPDFTBL_DEFAULT_SOURCE_ENCODING "UTF-8"
90
91 #define HPDFTBL_TEXT_HALIGN_LEFT 0
92 #define HPDFTBL_TEXT_HALIGN_CENTER 1
93 #define HPDFTBL_TEXT_HALIGN_RIGHT 2
94
95 /*
96 * Standard paper heights
97 */
98 #define A4PAGE_HEIGHT_CM 29.7
99 #define A4PAGE_WIDTH_CM 21.0
100 #define A3PAGE_HEIGHT_CM 42.0
101 #define A3PAGE_WIDTH_CM 29.7
102 #define LETTERRPAGE_HEIGHT_CM 27.9
103 #define LETTERRPAGE WIDTH CM 21.6
104 #define LEGALPAGE_HEIGHT_CM 35.6
105 #define LEGALPAGE_WIDTH_CM 21.6
110 #define HPDFTBL_END_CELLSPECS {0, 0, 0, 0, 0, 0, 0, 0, 0}
111
115 \ \#define \ HPDF\_COLOR\_FROMRGB(r, g, b) \ \ (HPDF\_RGBColor) \{(r)/255.0, (g)/255.0, (b)/255.0\} \\
116
120 #define MIN CALCULATED PERCENT CELL WIDTH 2.0
121
128 #define hpdftbl_cm2dpi(c) (((HPDF_REAL)(c))/2.54*72)
129
137 typedef enum hpdftbl_text_align {
        LEFT = 0,
138
        CENTER = 1.
139
        RIGHT = 2
140
141 } hpdftbl_text_align_t;
142
148 typedef struct text_style {
149
        char *font;
150
        HPDF REAL fsize;
151
        HPDF RGBColor color;
152
        HPDF_RGBColor background;
153
        hpdftbl_text_align_t halign;
154 } hpdf_text_style_t;
155
164 typedef char *(*hpdftbl_content_callback_t)(void *, size_t, size_t);
165
175 typedef void (*hpdftbl_canvas_callback_t) (HPDF_Doc, HPDF_Page, void *, size_t, size_t, HPDF_REAL,
       HPDF_REAL, HPDF_REAL,
176
                                                    HPDF_REAL);
177
187 typedef _Bool (*hpdftbl_content_style_callback_t)(void *, size_t, size_t, char *content,
       hpdf_text_style_t *);
188
192 typedef enum hpdftbl_dash_style {
193
        SOLID = 0,
        DOT1 = 1,
194
195
        DOT2 = 2
        DOT3 = 3,
196
197
        DASH1 = 4
```

14.4 hpdftbl.h 137

```
DASH2 = 5,
198
        DASH3 = 6,
DASHDOT = 7
199
200
201 } hpdftbl_line_style_t;
202
208 typedef struct border_style {
        HPDF_REAL width;
209
210
        HPDF_RGBColor color;
211
        hpdftbl_line_style_t line_style;
212 } hpdf_border_style_t;
213
221 struct hpdftbl_cell {
        char *label;
char *content;
223
225
227
        size_t colspan;
229
         size_t rowspan;
        HPDF_REAL height;
231
        HPDF_REAL width;
233
        HPDF_REAL delta_x;
235
237
        HPDF_REAL delta_y;
239
        HPDF_REAL textwidth;
241
        hpdftbl_content_callback_t content_cb;
243
        hpdftbl_content_callback_t label_cb;
        hpdftbl content style callback t style cb;
245
247
        hpdftbl_canvas_callback_t canvas_cb;
249
        hpdf_text_style_t content_style;
253
        struct hpdftbl_cell *parent_cell;
254 };
255
261 typedef struct hpdftbl_cell hpdftbl_cell_t;
262
271 struct hpdftbl {
273
        HPDF_Doc pdf_doc;
275
        HPDF_Page pdf_page;
277
        size_t cols;
279
        size t rows:
        HPDF_REAL posx;
281
        HPDF_REAL posy;
283
285
        HPDF_REAL height;
287
        HPDF_REAL width;
289
        void *tag;
291
        char *title txt;
        hpdf_text_style_t title_style;
hpdf_text_style_t header_style;
293
295
297
        _Bool use_header_row;
299
        hpdf_text_style_t label_style;
301
        _Bool use_cell_labels;
303
         _Bool use_label_grid_style;
305
        hpdftbl_content_callback_t label_cb;
        hpdf_text_style_t content_style;
307
        hpdftbl_content_callback_t content_cb;
309
311
        hpdftbl_content_style_callback_t content_style_cb;
313
        hpdftbl_canvas_callback_t canvas_cb;
        hpdftbl_cell_t *cells;
hpdf_border_style_t outer_border;
hpdf_border_style_t inner_border;
315
317
319
321
         float *col_width_percent;
322 };
323
332 typedef struct hpdftbl *hpdftbl_t;
333
343 typedef void (*hpdftbl_callback_t)(hpdftbl_t);
344
354 typedef struct hpdftbl_cell_spec {
356
        size_t row;
358
        size_t col;
360
        unsigned rowspan;
362
        unsigned colspan;
364
        char *label;
366
        hpdftbl_content_callback_t content_cb;
368
        hpdftbl_content_callback_t label_cb;
370
        hpdftbl_content_style_callback_t style_cb;
372
        hpdftbl_canvas_callback_t canvas_cb;
373 } hpdftbl_cell_spec_t;
374
381 typedef struct hpdftbl_spec {
        char *title;
383
385
        _Bool use_header;
387
        _Bool use_labels;
        _Bool use_labelgrid;
389
        size_t rows;
391
         size_t cols;
393
         HPDF_REAL xpos;
395
397
        HPDF_REAL ypos;
399
        HPDF_REAL width;
401
        HPDF_REAL height;
403
        hpdftbl_content_callback_t content_cb;
```

138 File Documentation

```
405
        hpdftbl_content_callback_t label_cb;
407
        hpdftbl_content_style_callback_t style_cb;
412
        hpdftbl_callback_t post_cb;
414
       hpdftbl_cell_spec_t *cell_spec;
415 } hpdftbl_spec_t;
416
423 typedef struct hpdftbl_theme {
425
        hpdf_text_style_t *content_style;
427
        hpdf_text_style_t *label_style;
        hpdf_text_style_t *header_style;
hpdf_text_style_t *title_style;
429
431
433
        hpdf_border_style_t *inner_border;
435
       hpdf_border_style_t *outer_border;
       _Bool use_labels;
437
439
       _Bool use_label_grid_style;
441
        _Bool use_header_row;
442 } hpdftbl_theme_t;
443
451 typedef void (*hpdftbl_error_handler_t)(hpdftbl_t, int, int, int);
453 static hpdftbl_error_handler_t hpdftbl_err_handler = NULL;
454
455 /*
456 * Table creation and destruction function 457 */
458 hpdftbl_t
459 hpdftbl_create(size_t rows, size_t cols);
460
461 hpdftbl_t
462 hpdftbl_create_title(size_t rows, size_t cols, char *title);
463
464 int
465 hpdftbl_stroke(HPDF_Doc pdf,
466
                   HPDF_Page page, hpdftbl_t t,
467
                   HPDF_REAL xpos, HPDF_REAL ypos,
                   HPDF_REAL width, HPDF_REAL height);
468
469
470 int
471 hpdftbl_stroke_from_data(HPDF_Doc pdf_doc, HPDF_Page pdf_page, hpdftbl_spec_t *tbl_spec, hpdftbl_theme_t
      *theme);
472
473 int.
474 hpdftbl_destroy(hpdftbl_t t);
475
476 int
477 hpdftbl_get_last_auto_height(HPDF_REAL *height);
478
479 void
480 hpdftbl_set_anchor_top_left(_Bool anchor);
481
482 _Bool
483 hpdftbl_get_anchor_top_left(void);
484
485 /*
486 \star Table error handling functions 487 \star/
488 hpdftbl_error_handler_t
489 hpdftbl_set_errhandler(hpdftbl_error_handler_t);
490
491 const char *
492 hpdftbl_get_errstr(int err);
493
494 const char
495 hpdftbl_hpdf_get_errstr(HPDF_STATUS err_code);
496
497 int
498 hpdftbl_get_last_errcode(const char **errstr, int *row, int *col);
499
500 void
501 hpdftbl_default_table_error_handler(hpdftbl_t t, int r, int c, int err);
502
503 /*
504 * Theme handling functions 505 */
506 int
507 hpdftbl_apply_theme(hpdftbl_t t, hpdftbl_theme_t *theme);
508
509 hpdftbl_theme_t *
510 hpdftbl_get_default_theme(void);
511
512 int
513 hpdftbl_destroy_theme(hpdftbl_theme_t *theme);
515 /*
516 * Table layout adjusting functions 517 */
518 int
```

14.4 hpdftbl.h 139

```
519 hpdftbl_set_colwidth_percent(hpdftbl_t t, size_t c, float w);
521 int
522 hpdftbl_clear_spanning(hpdftbl_t t);
523
524 int
525 hpdftbl_set_cellspan(hpdftbl_t t, size_t r, size_t c, size_t rowspan, size_t colspan);
526
527 /*
528 * Table style handling functions
529 */
530 int
531 hpdftbl_use_labels(hpdftbl_t t, _Bool use);
532
533 int
534 hpdftbl_use_labelgrid(hpdftbl_t t, _Bool use);
535
536 int
537 hpdftbl_set_background(hpdftbl_t t, HPDF_RGBColor background);
539 int
540 hpdftbl_set_outer_border(hpdftbl_t t, HPDF_REAL width, HPDF_RGBColor color);
541
542 int
543 hpdftbl_set_inner_border(hpdftbl_t t, HPDF_REAL width, HPDF_RGBColor color);
544
545 int
546 hpdftbl_set_header_style(hpdftbl_t t, char *font, HPDF_REAL fsize, HPDF_RGBColor color, HPDF_RGBColor
      background);
547
548 int
549 hpdftbl_set_header_halign(hpdftbl_t t, hpdftbl_text_align_t align);
550
551 int
552 hpdftbl_use_header(hpdftbl_t t, _Bool use);
553
554 int
555 hpdftbl_set_label_style(hpdftbl_t t, char *font, HPDF_REAL fsize, HPDF_RGBColor color, HPDF_RGBColor
       background);
556
557 int
558 hpdftbl_set_row_content_style(hpdftbl_t t, size_t r, char *font, HPDF_REAL fsize, HPDF_RGBColor color,
                                  HPDF_RGBColor background);
559
560
562 hpdftbl_set_col_content_style(hpdftbl_t t, size_t c, char *font, HPDF_REAL fsize, HPDF_RGBColor color,
563
                                  HPDF_RGBColor background);
564
565 int
566 hpdftbl_set_content_style(hpdftbl_t t, char *font, HPDF_REAL fsize, HPDF_RGBColor color, HPDF_RGBColor
      background);
567
568 int
569 hpdftbl_set_cell_content_style(hpdftbl_t t, size_t r, size_t c, char *font, HPDF_REAL fsize,
       HPDF RGBColor color.
570
                                   HPDF_RGBColor background);
571
572 int
573 hpdftbl_set_title_style(hpdftbl_t t, char *font, HPDF_REAL fsize, HPDF_RGBColor color, HPDF_RGBColor
       background);
574
575 /*
576 * Table content handling 577 */
578 int
579 hpdftbl_set_cell(hpdftbl_t t, int r, int c, char *label, char *content);
580
581 int
582 hpdftbl_set_tag(hpdftbl_t t, void *tag);
583
584 int
585 hpdftbl_set_title(hpdftbl_t t, char *title);
586
587 int
588 hpdftbl_set_title_halign(hpdftbl_t t, hpdftbl_text_align_t align);
590 int
591 hpdftbl_set_labels(hpdftbl_t t, char **labels);
592
593 int.
594 hpdftbl_set_content(hpdftbl_t t, char **content);
595
596 /
597 * Table callback functions
598 */
599 int.
600 hpdftbl_set_content_cb(hpdftbl_t t, hpdftbl_content_callback_t cb);
```

140 File Documentation

```
603 hpdftbl_set_cell_content_cb(hpdftbl_t t, size_t r, size_t c, hpdftbl_content_callback_t cb);
604
605 int
606 hpdftbl_set_cell_content_style_cb(hpdftbl_t t, size_t r, size_t c, hpdftbl_content_style_callback_t cb);
608 int
609 hpdftbl_set_content_style_cb(hpdftbl_t t, hpdftbl_content_style_callback_t cb);
610
611 int
612 hpdftbl_set_label_cb(hpdftbl_t t, hpdftbl_content_callback_t cb);
613
615 hpdftbl_set_cell_label_cb(hpdftbl_t t, size_t r, size_t c, hpdftbl_content_callback_t cb);
616
617 int
618 hpdftbl_set_canvas_cb(hpdftbl_t t, hpdftbl_canvas_callback_t cb);
619
621 hpdftbl_set_cell_canvas_cb(hpdftbl_t t, size_t r, size_t c, hpdftbl_canvas_callback_t cb);
622
623 /*
624 * Text encoding
625 */
626 void
627 hpdftbl_set_text_encoding(char *target, char *source);
628
629 int
630 hpdftbl_encoding_text_out(HPDF_Page page, HPDF_REAL xpos, HPDF_REAL ypos, char *text);
631
632 /*
633 * Misc utility and widget functions
634 */
635
636 void
637 HPDF RoundedCornerRectangle(HPDF Page page, HPDF REAL xpos, HPDF REAL ypos, HPDF REAL width, HPDF REAL
       height,
638
                                  HPDF REAL rad):
639
640 void
641 hpdftbl_stroke_grid(HPDF_Doc pdf, HPDF_Page page);
642
643 void
644 hpdftbl_table_widget_letter_buttons(HPDF_Doc doc, HPDF_Page page,
645
                                          HPDF_REAL xpos, HPDF_REAL ypos, HPDF_REAL width, HPDF_REAL height,
646
                                          HPDF_RGBColor on_color, HPDF_RGBColor off_color,
647
                                          {\tt HPDF\_RGBColor\ on\_background,\ HPDF\_RGBColor\ off\_background,}
648
                                          HPDF REAL fsize.
649
                                          const char *letters, Bool *state);
650
651 void
652 hpdftbl_widget_slide_button(HPDF_Doc doc, HPDF_Page page,
                                 HPDF_REAL xpos, HPDF_REAL ypos, HPDF_REAL width, HPDF_REAL height, _Bool
       state);
654
655 void
656 hpdftbl_widget_hbar(HPDF_Doc doc, HPDF_Page page,
657
                         HPDF_REAL xpos, HPDF_REAL ypos, HPDF_REAL width, HPDF_REAL height,
658
                         HPDF_RGBColor color, float val, _Bool hide_val);
659
660 void
661 hpdftbl_widget_segment_hbar(HPDF_Doc doc, HPDF_Page page,
                                 HPDF_REAL xpos, HPDF_REAL ypos, HPDF_REAL width, HPDF_REAL height,
663
                                  size_t num_segments, HPDF_RGBColor on_color, double val_percent,
664
                                 _Bool hide_val);
665
666 void
667 hpdftbl_widget_strength_meter(HPDF_Doc doc, HPDF_Page page,
                                   HPDF_REAL xpos, HPDF_REAL ypos, HPDF_REAL width, HPDF_REAL height, size_t num_segments, HPDF_RGBColor on_color, size_t num_on_segments);
669
670
671 #ifdef
              __cplusplus
672 }
673 #endif
              /* hpdftbl_H */
675 #endif
```

# 14.5 /Users/ljp/Devel/hpdf\_table/src/hpdftbl\_errstr.c File Reference

Utility module to translate HPDF error codes to human readable strings.

```
#include <hpdf.h>
```

## **Data Structures**

struct hpdftbl\_errcode\_entry
 An entry in the error string table.

## **Functions**

const char \* hpdftbl\_hpdf\_get\_errstr (const HPDF\_STATUS err\_code)
 Function to return a human readable error string for an error code from Core HPDF library.

## 14.5.1 Detailed Description

Utility module to translate HPDF error codes to human readable strings.

#### 14.5.2 Function Documentation

#### 14.5.2.1 hpdftbl\_hpdf\_get\_errstr()

Function to return a human readable error string for an error code from Core HPDF library.

The various error codes given by the HPDF library can be translated back to a string by the usage of this function. The function will return a pointer to a static string that can not be manipulated.

#### **Parameters**

```
err_code The error code
```

#### Returns

A pointer to an error string, NULL if the error code is invalid

#### See also

hpdftbl\_get\_errstr()

# 14.6 /Users/ljp/Devel/hpdf\_table/src/hpdftbl\_grid.c File Reference

Create a grid on a document for positioning.

142 File Documentation

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <hpdf.h>
```

## **Functions**

• void hpdftbl\_stroke\_grid (HPDF\_Doc pdf, HPDF\_Page page)

## 14.6.1 Detailed Description

Create a grid on a document for positioning.

## 14.6.2 Function Documentation

## 14.6.2.1 hpdftbl\_stroke\_grid()

Stroke a point grid on specified page to make it easier to position text and tables.

#### **Parameters**

pdf	Document handle
page	Page handle

# 14.7 /Users/Ijp/Devel/hpdf\_table/src/hpdftbl\_widget.c File Reference

## Support for drawing widgets.

```
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <hpdf.h>
#include <string.h>
#include <math.h>
#include "hpdftbl.h"
```

## **Macros**

- #define TRUE 1
- #define FALSE 0

#### **Functions**

void hpdftbl\_table\_widget\_letter\_buttons (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF
\_REAL ypos, HPDF\_REAL width, HPDF\_REAL height, const HPDF\_RGBColor on\_color, const HPDF\_
RGBColor off\_color, const HPDF\_RGBColor on\_background, const HPDF\_RGBColor off\_background, const HPDF\_REAL fsize, const char \*letters, Bool \*state)

Display an array of letters as a table where each letter is its own "mini" cell and sorrounded by a frame. Each boxed letter can be in an "on" state or "off" state which is illustrated with different font and fac colors.

• void hpdftbl\_widget\_slide\_button (HPDF\_Doc doc, HPDF\_Page page, HPDF\_REAL xpos, HPDF\_REAL xpos, HPDF\_REAL width, HPDF\_REAL height, \_Bool state)

Table widget that draws a sliding on/off switch. Meant to be used in a canvas callback to display a boolean value.

 void hpdftbl\_widget\_hbar (const HPDF\_Doc doc, const HPDF\_Page page, const HPDF\_REAL xpos, const HPDF\_REAL ypos, const HPDF\_REAL width, const HPDF\_REAL height, const HPDF\_RGBColor color, const float val, const \_Bool hide\_val)

Draw a horizontal partially filled bar to indicate an analog (percentage) value.

void hpdftbl\_widget\_segment\_hbar (const HPDF\_Doc doc, const HPDF\_Page page, const HPDF\_REAL xpos, const HPDF\_REAL ypos, const HPDF\_REAL width, const HPDF\_REAL height, const size\_t num
 \_\_segments, const HPDF\_RGBColor on\_color, const double val\_percent, const \_Bool hide\_val)

Draw a horizontal segment meter that can be used to visualize a discrete value.

Draw a phone strength meter.

## 14.7.1 Detailed Description

Support for drawing widgets.

### 14.7.2 Function Documentation

#### 14.7.2.1 hpdftbl\_table\_widget\_letter\_buttons()

Display an array of letters as a table where each letter is its own "mini" cell and sorrounded by a frame. Each boxed letter can be in an "on" state or "off" state which is illustrated with different font and fac colors.

144 File Documentation

#### **Parameters**

doc	HPDF document handle
page	HPDF page handle
xpos	X-öosition of cell
ypos	Y-Position of cell
width	Width of cell
height	Height of cell
on_color	The font color in "on" state
off_color	The font color in "off" state
on_background	The face color in "on" state
off_background	The face color in "off" state
fsize	The font size
letters	What letters to have in the boxes
state	What state each boxed letter should be (0=off, 1=pn)

## 14.7.2.2 hpdftbl\_widget\_hbar()

Draw a horizontal partially filled bar to indicate an analog (percentage) value.

This function can not be used directly as a canvas callback since it needs additional parameters. Instead create a simple canvas callback that gives the additional parameters.

### **Parameters**

doc	HPDF Document handle
page	HPDF Page handle
xpos	Lower left x
ypos	Lower left y
width	Width of meter
height	Height of meter
color	Fill color for bar
val	Percentage fill in range [0.0, 100.0]
show_val	TRUE to show the value (in percent) at the right end of the entire bar

## 14.7.2.3 hpdftbl\_widget\_segment\_hbar()

Draw a horizontal segment meter that can be used to visualize a discrete value.

This function can not be used directly as a canvas callback since it needs additional parameters. Instead create a simple canvas callback that gives the additional parameters.

#### **Parameters**

doc	HPDF Document handle
page	HPDF Page handle
xpos	Lower left x
ypos	Lower left y
width	Width of meter
height	Height of meter
num_segments	Total number of segments
on_color	Color for "on" segment
num_on_segments	Number of on segments

## 14.7.2.4 hpdftbl\_widget\_slide\_button()

Table widget that draws a sliding on/off switch. Meant to be used in a canvas callback to display a boolean value.

This function can not be used directly as a canvas callback since it needs the state of the button as an argument. Instead create a simple canvas callback that determines the wanted state and then just passes on all argument to this widget function.

#### **Parameters**

doc	HPDF document handle

146 File Documentation

#### **Parameters**

page	HPDF page handle
xpos	X-öosition of cell
ypos	Y-Position of cell
width	Width of cell
height	Height of cell
state	State of button On/Off

## 14.7.2.5 hpdftbl\_widget\_strength\_meter()

## Draw a phone strength meter.

This function can not be used directly as a canvas callback since it needs additional parameters. Instead create a simple canvas callback that gives the additional parameters.

#### **Parameters**

doc	HPDF Document handle
page	HPDF Page handle
xpos	Lower left x
ypos	Lower left y
width	Width of meter
height	Height of meter
num_segments	Total number of segments
on_color	Color for "on" segment
num_on_segments	Number of on segments

# **Chapter 15**

# **Example Documentation**

# 15.1 tut\_ex01.c

The very most basic table with API call to set content in each cell.

```
/* tut_ex01 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex01.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex01.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
#// Silent gcc about unused "arg" in the callback and error functions #pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
//\ A standard hpdf error handler which also translates the hpdf error code to a //\ human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
     void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
                hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
     longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
create_table_ex01(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
     const size_t num_rows = 2;
const size_t num_cols = 2;
     //char *table_title = "tut_ex01: 2x2 table";
hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
     hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
hpdftbl_set_cell(tbl, 0, 0, NULL, "Cell 0x0");
hpdftbl_set_cell(tbl, 0, 1, NULL, "Cell 0x1");
hpdftbl_set_cell(tbl, 1, 0, NULL, "Cell 1x0");
hpdftbl_set_cell(tbl, 1, 1, NULL, "Cell 1x1");
// We have to specify the top left position on the PDF as well as the width.
// We let the library automatically determine the height of the table based
     // on the font and number of rows.
```

```
HPDF_REAL xpos = hpdftbl_cm2dpi(1);
     HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
     HPDF_REAL width = hpdftbl_cm2dpi(5);
HPDF_REAL height = 0; // Calculate height automatically
     // Stroke the table to the page
     hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one age
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
     /// Setup the basic PDF document
*pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
     HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
     HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
     if (addgrid) {
          hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
      fprintf(stderr, "ERROR: Cannot save to file!");
}
     HPDF_Free (pdf_doc);
     printf("Done.\n");
#ifndef MSC VER
// Silent gcc about unused "arg" in the callback and error functions #pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
main(int argc, char **argv) {
     HPDF_Doc pdf_doc;
     HPDF_Page pdf_page;
     if (setjmp(env)) {
         HPDF_Free (pdf_doc);
          return EXIT_FAILURE;
     setup_hpdf(&pdf_doc, &pdf_page, FALSE);
create_table_ex01(pdf_doc, pdf_page);
     stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
     return EXIT_SUCCESS;
#ifndef MSC VER
#pragma GCC diagnostic pop
#endif
```

# 15.2 tut ex02.c

Basic table with content data specified as an array.

```
/* tut_ex01 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32___)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#iff!(defined_WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex02.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex02.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
```

15.2 tut ex02.c 149

```
jmp_buf env;
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
     void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
              hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
     longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
typedef char **content t;
void setup_dummy_data(content_t *content, size_t rows, size_t cols) {
    char buff[255]:
     *content = calloc(rows*cols, sizeof(char*));
     size_t cnt = 0;
    for (size_t r = 0; r < rows; r++) {
    for (size_t c = 0; c < cols; c++) {
        snprintf(buff, sizeof(buff), "Content %zu", cnt);
        (*content)[cnt] = strdup(buff);</pre>
         }
    }
}
void
create_table_ex02(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 2;
const size_t num_cols = 2;
    //char *table_title = "tut_ex01: 2x2 table";
hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
     content t content;
     setup_dummy_data(&content, 2, 2);
     hpdftbl_set_content(tbl, content);
     HPDF_REAL xpos = hpdftbl_cm2dpi(1);
     HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(5);
HPDF_REAL height = 0; // Calculate height automatically
     // Stroke the table to the page
     hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
     // Setup the basic PDF document
     *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
     {\tt HPDF\_SetCompressionMode(\star pdf\_doc,\ HPDF\_COMP\_ALL);}
     HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
     if (addgrid) {
         hpdftbl stroke grid(*pdf doc, *pdf page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
      fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
main(int argc, char **argv) {
     HPDF_Doc pdf_doc;
     HPDF_Page pdf_page;
     if (setjmp(env)) {
         HPDF_Free (pdf_doc);
         return EXIT FAILURE;
     setup_hpdf(&pdf_doc, &pdf_page, FALSE);
    create_table_ex02(pdf_doc, pdf_page);
     stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
     return EXIT_SUCCESS;
}
```

```
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# 15.3 tut\_ex03.c

First example with API call to set content in each cell with added labels and shortened grid.

```
/* tut_ex01 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#if !(defined WIN32 || defined WIN32 )
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex03.pdf"
#define OUTPUT_FILE "/tmp/tut_ex03.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
     void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
               hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
     longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
void
create table ex03(HPDF Doc pdf doc, HPDF Page pdf page) {
    const size_t num_rows = 2;
const size_t num_cols = 2;
     //char *table_title = "tut_ex01: 2x2 table";
     hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
hpdftbl set cell(tbl, 0, 0, "Label 1", "Cell 0x0");
    hpdftbl_set_cell(tbl, 0, 0, "Label 1", "Cell 0x0");
hpdftbl_set_cell(tbl, 0, 1, "Label 2", "Cell 0x1");
hpdftbl_set_cell(tbl, 0, 1, "Label 2", "Cell 0x1");
hpdftbl_set_cell(tbl, 1, 0, "Label 3", "Cell 1x0");
hpdftbl_set_cell(tbl, 1, 1, "Label 4", "Cell 1x1");
hpdftbl_use_labels(tbl, TRUE);
     hpdftbl_use_labelgrid(tbl, FALSE);
     // We have to specify the top left position on the PDF as well as the width. // We let the library automatically determine the height of the table based
     // on the font and number of rows.
     HPDF_REAL xpos = hpdftbl_cm2dpi(1);
     HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
     HPDF_REAL width = hpdftbl_cm2dpi(5);
HPDF_REAL height = 0; // Calculate height automatically
// Stroke the table to the page
     hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one age
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
     // Setup the basic PDF document
*pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
     HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
     HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
     if (addgrid) {
          hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
```

15.4 tut\_ex05.c 151

```
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
      fprintf(stderr, "ERROR: Cannot save to file!");
     HPDF_Free (pdf_doc);
     printf("Done.\n");
#ifndef MSC VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int
main(int argc, char **argv) {
     HPDF_Doc pdf_doc;
     HPDF_Page pdf_page;
     if (setjmp(env)) {
    HPDF_Free(pdf_doc);
          return EXIT_FAILURE;
     setup_hpdf(&pdf_doc, &pdf_page, FALSE);
     create_table_ex03(pdf_doc, pdf_page);
     stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
     return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# 15.4 tut\_ex05.c

Set content data specified as an array with added labels and shortened grid.

```
/* tut_ex05 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#iff!(defined_WIN32 || defined__WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file \# ifdef \ \_WIN32
#define OUTPUT_FILE "tut_ex05.pdf"
#define OUTPUT_FILE "/tmp/tut_ex05.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions 
#pragma GCC diagnostic push 
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
    longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

```
typedef char **content_t;
void setup_dummy_data(content_t *content, content_t *labels, size_t rows, size_t cols) {
     char buff[255];
     *content = calloc(rows*cols, sizeof(char*));
*labels = calloc(rows*cols, sizeof(char*));
     size_t cnt = 0;
     for (size_t r = 0; r < rows; r++) {</pre>
          for (size_t c = 0; c < cols; c++) {
    snprintf(buff, sizeof(buff), "Content %zu", cnt);</pre>
               (*content)[cnt] = strdup(buff);
snprintf(buff, sizeof(buff), "Label %zu", cnt);
(*labels)[cnt] = strdup(buff);
               cnt++;
          }
     }
void
create_table_ex04(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 2;
     const size_t num_cols = 2;
     char *table_title = "tut_ex05: 2x2 table";
     hpdftbl_t tbl = hpdftbl_create_title(num_rows, num_cols, table_title);
     content_t content, labels;
     setup_dummy_data(&content, &labels, num_rows, num_cols);
hpdftbl_set_content(tbl, content);
hpdftbl_set_labels(tbl, labels);
     hpdftbl_use_labels(tbl, TRUE);
     hpdftbl_use_labelgrid(tbl, TRUE);
     HPDF_REAL ypos = hpdftbl_cm2dpi(1);
HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
HPDF_REAL width = hpdftbl_cm2dpi(5);
HPDF_REAL height = 0; // Calculate height automatically
     // Stroke the table to the page
     hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
     // Setup the basic PDF document
     *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
     HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
     HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
     if (addgrid) {
          hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
}
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file))
          fprintf(stderr, "ERROR: Cannot save to file!");
     HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int
main(int argc, char **argv) {
     HPDF_Doc pdf_doc;
     HPDF_Page pdf_page;
     if (setjmp(env)) {
    HPDF_Free(pdf_doc);
          return EXIT_FAILURE;
     setup_hpdf(&pdf_doc, &pdf_page, FALSE);
     create_table_ex04(pdf_doc, pdf_page);
     stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

15.5 tut ex06.c 153

# 15.5 tut ex06.c

Use content to set content and labels.

```
/* tut_ex06 *
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT FILE "tut ex06.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex06.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
                         void *user_data) {
    longjmp(env, 1);
static char *
cb_date(void *tag, size_t r, size_t c) {
    static char buf[64];
    time_t t = time(NULL);
    ctime_r(&t, buf);
    return buf;
static char *
cb_content(void *tag, size_t r, size_t c) {
   static char buf[32];
#if (defined _WIN32 | | defined _WIN32_)
snprintf(buf, sizeof buf, "Content %02i x %02i", r, c);
#else
   snprintf(buf, sizeof buf, "Content %02zu x %02zu", r, c);
#endif
   return buf;
static char *
cb_labels(void *tag, size_t r, size_t c) {
   static char buf[32];
#if (defined _WIN32 || defined __WIN32__)
    if (0==r && 0==c) {
       snprintf(buf, sizeof buf, "Date:");
    } else {
       snprintf(buf, sizeof buf, "Label %ix%i:", r, c);
#else
    if (0==r && 0==c) {
       snprintf(buf, sizeof buf, "Date:");
    } else {
       snprintf(buf, sizeof buf, "Label %zux%zu:", r, c);
#endif
   return buf;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
create_table_ex06(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
   const size_t num_rows = 2;
```

```
const size_t num_cols = 2;
     char *table_title = "tut_ex06: 2x2 table with callbacks";
     hpdftbl_t tbl = hpdftbl_create_title(num_rows, num_cols, table_title);
     hpdftbl_use_labels(tbl, TRUE);
     hpdftbl_use_labelgrid(tbl, TRUE);
     hpdftbl_set_content_cb(tbl, cb_content);
     hpdftbl_set_label_cb(tbl, cb_labels);
     hpdftbl_set_cell_content_cb(tbl, 0, 0, cb_date);
     HPDF_REAL xpos = hpdftbl_cm2dpi(1);
HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
     HPDF_REAL width = hpdftbl_cm2dpi(12);
HPDF_REAL height = 0; // Calculate height automatically
     // Stroke the table to the page
     hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
    // Setup the basic PDF document
     *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
     HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
     {\tt HPDF\_Page\_SetSize(*pdf\_page, HPDF\_PAGE\_SIZE\_A4, HPDF\_PAGE\_PORTRAIT);}
     if (addgrid) {
         hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
biov
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
      fprintf(stderr, "ERROR: Cannot save to file!");
     HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
main(int argc, char **argv) {
     HPDF_Doc pdf_doc;
     HPDF_Page pdf_page;
     if (setjmp(env)) {
    HPDF_Free(pdf_doc);
         return EXIT FAILURE:
     setup_hpdf(&pdf_doc, &pdf_page, FALSE);
     create_table_ex06(pdf_doc, pdf_page);
     stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
     return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# 15.6 tut\_ex07.c

## Expand cells over multiple columns and rows.

```
/* tut_ex07 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
\ensuremath{//} The output after running the program will be written to this file
```

15.6 tut ex07.c 155

```
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex07.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex07.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a // human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
    void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
             hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
    longjmp(env, 1);
static char *
cb_date(void *tag, size_t r, size_t c) {
   static char buf[64];
    time_t t = time(NULL);
    ctime_r(&t, buf);
    return buf;
static char *
cb_content(void *tag, size_t r, size_t c) {
    static char buf[32];
#if (defined _WIN32 || defined ___WIN32_
    snprintf(buf, sizeof buf, "Content %02ix%02i", r, c);
#else
    snprintf(buf, sizeof buf, "Content %02zux%02zu", r, c);
#endif
    return buf;
static char *
cb_labels(void *tag, size_t r, size_t c) {
    static char buf[32];
#if (defined _WIN32 || defined __WIN32__)
    if (0==r && 0==c) {
         snprintf(buf, sizeof buf, "Date:");
    } else {
        snprintf(buf, sizeof buf, "Label %ix%i:", r, c);
    }
#else
    if (0==r && 0==c) {
         snprintf(buf, sizeof buf, "Date:");
    } else
        snprintf(buf, sizeof buf, "Label %zux%zu:", r, c);
#endif
    return buf;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
void
create_table_ex07(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
   const size_t num_rows = 7;
const size_t num_cols = 5;
    char *table_title = "tut_ex07: 7x5 table with row and colspans";
hpdftbl_t tbl = hpdftbl_create_title(num_rows, num_cols, table_title);
hpdftbl_use_labels(tbl, TRUE);
    hpdftbl_use_labelgrid(tbl, TRUE);
    hpdftbl_set_content_cb(tbl, cb_content);
    hpdftbl_set_label_cb(tbl, cb_labels);
    hpdftbl_set_cell_content_cb(tbl, 0, 0, cb_date);
    hpdftbl_set_cellspan(tbl, 0, 0, 1, 3);
hpdftbl_set_cellspan(tbl, 2, 2, 3, 3);
    hpdftbl_set_cellspan(tbl, 3, 0, 4, 1);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(18);
HPDF_REAL height = 0; // Calculate height automatically
// Stroke the table to the page
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
     // Setup the basic PDF document
    *pdf_doc = HPDF_New(error_handler, NULL);
```

```
*pdf_page = HPDF_AddPage(*pdf_doc);
    HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
    HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
    if (addgrid) {
         hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
    printf("Sending to file \"%s\" ...\n", file);
if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
    fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef MSC VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
main(int argc, char **argv) {
    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env))
         HPDF_Free (pdf_doc);
         return EXIT_FAILURE;
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
    create_table_ex07(pdf_doc, pdf_page);
    stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
```

# 15.7 tut\_ex08.c

Adjust column width and expand cells over multiple columns and rows.

```
/* tut_ex08 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if ! (defined __WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex08.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex08.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
    void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
```

15.7 tut ex08.c 157

```
hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
    longjmp(env, 1);
static char *
cb_date(void *tag, size_t r, size_t c) {
    static char buf[64];
    time_t t = time(NULL);
    ctime_r(&t, buf);
    return buf;
static char *
cb_content(void *tag, size_t r, size_t c) {
    static char buf[32];
#if (defined _WIN32 || defined _WIN32_)
snprintf(buf, sizeof buf, "Content %2ix%2i", r, c);
    snprintf(buf, sizeof buf, "Content %zux%zu", r, c);
#endif
    return buf;
static char *
cb_labels(void *tag, size_t r, size_t c) {
    static char buf[32];
#if (defined _WIN32 || defined __WIN32__)
    if (0==r && 0==c) {
         snprintf(buf, sizeof buf, "Date:");
    } else {
        snprintf(buf, sizeof buf, "Label %ix%i:", r, c);
#else
    if (0==r && 0==c) {
         snprintf(buf, sizeof buf, "Date:");
         snprintf(buf, sizeof buf, "Label %zux%zu:", r, c);
#endif
    return buf;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
void
create_table_ex08(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
const size_t num_cols = 4;
     char *table_title = "tut_ex08: 4x4 adjusting col width";
    hpdftbl_t tbl = hpdftbl_create_title(num_rows, num_cols, table_title);
    hpdftbl_use_labels(tbl, TRUE);
    hpdftbl_use_labelgrid(tbl, TRUE);
hpdftbl_set_content_cb(tbl, cb_content);
    hpdftbl_set_label_cb(tbl, cb_labels);
    hpdftbl_set_cell_content_cb(tbl, 0, 0, cb_date);
hpdftbl_set_cellspan(tbl, 0, 0, 1, 3);
    hpdftbl_set_colwidth_percent(tbl, 0,40);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
HPDF_REAL width = hpdftbl_cm2dpi(17);
    HPDF_REAL height = 0; // Calculate height automatically
     // Stroke the table to the page
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
^{\prime} // Setup a new PDF document with one page
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
     // Setup the basic PDF document
    *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
    *Put_page = HFDF_Audrage(*put_uoc),
HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
    if (addgrid) {
         hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
    printf("Sending to file \"%s\" ...\n", file);
    if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file))
         fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF Free (pdf doc):
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
```

```
int
main(int argc, char **argv) {

    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env)) {
        HPDF_Free(pdf_doc);
        return EXIT_FAILURE;
    }
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
    create_table_ex08(pdf_doc, pdf_page);

    stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
}
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

## 15.8 tut ex09.c

#### Adjusting font style with a callback.

```
/* tut_ex09 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex09.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex09.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
    void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
            hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
    longjmp(env, 1);
}
_Bool
cb_style(void *tag, size_t r, size_t c, char *content, hpdf_text_style_t *style) {
    // Format the header row/column with a grey background and Helvetica font while the rest of the
    // table uses "Times Roman"
    if( 0==r || 0==c ) { // Headers
    style->font = HPDF_FF_HELVETICA_BOLD;
        style->fsize = 12;
style->color = COLOR_BLACK;
        style->background = COLOR_LIGHT_GRAY;
        if ( c > 0 )
             style->halign = CENTER;
        else
            style->halign = LEFT;
    } else { // Content
        style->font = HPDF_FF_TIMES;
        style->fsize = 11;
style->color = COLOR_BLACK;
        style->background = COLOR_WHITE;
```

15.8 tut ex09.c 159

```
style->halign = CENTER;
    return TRUE;
static char *
cb_content(void *tag, size_t r, size_t c) {
    static char buf[32];
    if( 0==r && 0==c ) return NULL;
if( 0==c ) {
#if (defined _WIN32 || defined _
        fined _WIN32 || defined _WIN32_)
snprintf(buf, sizeof buf, "Extra long Header %2ix%2i", r, c);
        snprintf(buf, sizeof buf, "Extra long Header %zux%zu", r, c);
#endif
      else if( 0==r ) {
#else
        snprintf(buf, sizeof buf, "Header %zux%zu", r, c);
#endif
      else {
#else
        snprintf(buf, sizeof buf, "Content %zux%zu", r, c);
#endif
    return buf;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
create_table_ex09(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
const size_t num_cols = 4;
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    hpdftbl_set_content_cb(tbl, cb_content);
    hpdftbl_set_content_style_cb(tbl, cb_style);
    hpdftbl_set_colwidth_percent(tbl, 0, 40);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 4);
    HPDF_REAL height = 0; // Calculate height automatically // Stroke the table to the page
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
^{\prime} // Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
    // Setup the basic PDF document
    *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
    HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
    HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
    if (addgrid) {
        hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
biov
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file))
        fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int
main(int argc, char **argv) {
    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env)) {
        HPDF_Free (pdf_doc);
        return EXIT FAILURE;
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
    create_table_ex09(pdf_doc, pdf_page);
    stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
```

```
}
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# 15.9 tut\_ex10.c

Adjust column widths and add error handler.

```
/* tut_ex10 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
#include <syslog.h>
// This include should always be used #include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex10.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex10.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
\ensuremath{//}\ A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
// Haman Teadable String
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no, void *user_data) {
    fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
              hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
     longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
typedef char **content_t;
void setup_dummy_data(content_t *content, size_t rows, size_t cols) {
    char buff[255];
    *content = calloc(rows*cols, sizeof(char*));
size_t cnt = 0;
     for (size_t r = 0; r < rows; r++) {
    for (size_t c = 0; c < cols; c++) {
        snprintf(buff, sizeof(buff), "Content %zu", cnt);
    }
}</pre>
               (*content)[cnt] = strdup(buff);
              cnt++;
         }
    }
create_table_ex10(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
const size_t num_cols = 4;
     hpdftbl_set_errhandler(hpdftbl_default_table_error_handler);
     hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
     hpdftbl_set_colwidth_percent(tbl, 0, 40);
     hpdftbl_set_colwidth_percent(tbl, 1, 70);
     content_t content;
     setup_dummy_data(&content, num_rows, num_cols);
     hpdftbl_set_content(tbl, content);
HPDF_REAL xpos = hpdftbl_cm2dpi(1);
     HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 4);
HPDF_REAL height = 0; // Calculate height automatically
     // Stroke the table to the page
```

15.10 tut ex11.c 161

```
hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
^{\prime} // Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
   // Setup the basic PDF document
   *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
     HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
     HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
     if (addgrid) {
          hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
      fprintf(stderr, "ERROR: Cannot save to file!");
     HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef MSC VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int
main(int argc, char **argv) {
     HPDF_Doc pdf_doc;
     HPDF_Page pdf_page;
     if (setjmp(env))
         HPDF_Free (pdf_doc);
         closelog();
          return EXIT_FAILURE;
     setup_hpdf(&pdf_doc, &pdf_page, FALSE);
     create_table_ex10(pdf_doc, pdf_page);
     stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
     return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
```

# 15.10 tut\_ex11.c

Table with header row and error handler.

```
/* tut ex11 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
#include <syslog.h>
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex11.pdf"
#define OUTPUT_FILE "/tmp/tut_ex11.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
```

```
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no, void *user_data) {
    fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d\\n",
hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
    longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
typedef char **content_t;
void setup_dummy_data(content_t *content, size_t rows, size_t cols) {
    char buff[255];
    *content = calloc(rows*cols, sizeof(char*));
    size_t cnt = 0;
    for (size_t r = 0; r < rows; r++) {
    for (size_t c = 0; c < cols; c++) {
        snprintf(buff, sizeof(buff), "Content %zu", cnt);
    }
}</pre>
              (*content)[cnt] = strdup(buff);
              cnt++;
         }
    }
}
void
create_table_ex11(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
    const size_t num_rows = 4;
const size_t num_cols = 4;
    \verb|hpdftbl_set_errhandler(hpdftbl_default_table_error_handler);|\\
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
hpdftbl_use_header(tbl, TRUE);
    hpdftbl_set_colwidth_percent(tbl, 0, 40);
    content_t content;
    setup_dummy_data(&content, num_rows, num_cols);
    hpdftbl_set_content(tbl, content);
HPDF_REAL xpos = hpdftbl_cm2dpi(1);
    HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 5);
    HPDF_REAL height = 0; // Calculate height automatically
    // Stroke the table to the page
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
^{\prime} // Setup a new PDF document with one page
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
    // Setup the basic PDF document
    *pdf_doc = HPDF_New(error_handler, NULL);
    *pdf_page = HPDF_AddPage(*pdf_doc);
    HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
    HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
         hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
    printf("Sending to file \"%s\" ...\n", file);
if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file))
         fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
main(int argc, char **argv) {
    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env)) {
         HPDF_Free (pdf_doc);
         closelog();
         return EXIT_FAILURE;
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
create_table_ex11(pdf_doc, pdf_page);
stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

15.11 tut\_ex12.c 163

# 15.11 tut ex12.c

Table with header row and error handler.

```
/* tut_ex12 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
#include <syslog.h>
// This include should always be used
#include "../src/hpdftbl.h"
\ensuremath{//} The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex12.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex12.pdf"
#define TRUE 1
#define FALSE 0
// For simulated exception handling
imp buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no, void *user_data) {
    longjmp(env, 1);
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
typedef char **content t;
void setup_dummy_data(content_t *content, size_t rows, size_t cols) {
    char buff[255];
    *content = calloc(rows*cols, sizeof(char*));
    size_t cnt = 0;
    for (size_t r = 0; r < rows; r++) {</pre>
        for (size_t c = 0; c < cols; c++) {
    snprintf(buff, sizeof(buff), "Content %zu", cnt);
    (*content)[cnt] = strdup(buff);</pre>
            cnt++;
        }
    }
void
create_table_ex12(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
   const size_t num_rows = 4;
    const size_t num_cols = 4;
    hpdftbl_set_errhandler(hpdftbl_default_table_error_handler);
    hpdftbl_t tbl = hpdftbl_create(num_rows, num_cols);
    hpdftbl_use_header(tbl, TRUE);
    hpdftbl_set_colwidth_percent(tbl, 0, 40);
    content_t content;
    setup_dummy_data(&content, num_rows, num_cols);
    hpdftbl_set_content(tbl, content);
    HPDF_REAL xpos = hpdftbl_cm2dpi(1);
HPDF_REAL ypos = hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM - 1);
    HPDF_REAL width = hpdftbl_cm2dpi(A4PAGE_WIDTH_CM - 5);
HPDF_REAL height = 0; // Calculate height automatically
    // Stroke the table to the page
    hpdftbl_stroke(pdf_doc, pdf_page, tbl, xpos, ypos, width, height);
// Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
    // Setup the basic PDF document
    *pdf_doc = HPDF_New(error_handler, NULL);
    *pdf_page = HPDF_AddPage(*pdf_doc);
    HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
```

```
HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
    if (addgrid) {
        hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file)
    printf("Sending to file \"%s\" ...\n", file);
    if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file))
         fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int
main(int argc, char **argv) {
    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env)) {
        HPDF_Free (pdf_doc);
        closelog();
        return EXIT_FAILURE;
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
create_table_ex12(pdf_doc, pdf_page);
stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# 15.12 tut\_ex13\_1.c

Defining a table with a data structure for the table.

```
/* tut_ex13_1 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
#include "../src/hpdftbl.h"
// The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex13_1.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex13_1.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
static void error_handler(HPDF_STATUS error_no, HPDF_STATUS detail_no,
    void *user_data) {
fprintf(stderr, "*** PDF ERROR: \"%s\", [0x%04X : %d]\n",
            hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
    longjmp(env, 1);
```

15.12 tut ex13 1.c 165

```
static char *
cb_content(void *tag, size_t r, size_t c) {
    static char buf[32];
#if (defined _WIN32 || defined __WIN32__)
    if(0==r)
        snprintf(buf, sizeof buf, "Header %02ix%02i", r, c);
         snprintf(buf, sizeof buf, "Content %02ix%02i", r, c);
    if( 0==r )
         snprintf(buf, sizeof buf, "Header %02zux%02zu", r, c);
    else
        snprintf(buf, sizeof buf, "Content %02zux%02zu", r, c);
#endif
    return buf;
static char *
cb_label(void *tag, size_t r, size_t c) {
    static char buf[32];
#if (defined _WIN32 || defined __WIN32__)
    if (0==r && 0==c) {
         snprintf(buf, sizeof buf, "Date:");
    } else {
        snprintf(buf, sizeof buf, "Label %ix%i:", r, c);
    }
#else
     if (0==r && 0==c) {
         snprintf(buf, sizeof buf, "Date:");
    } else {
        snprintf(buf, sizeof buf, "Label %zux%zu:", r, c);
#endif
    return buf;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
hpdftbl_spec_t tbl_spec = {
         // Title and header flag
         .title=NULL, .use_header=TRUE,
         // Label and labelgrid flags
         .use_labels=FALSE, .use_labelgrid=FALSE,
         // Row and columns
         .rows=4, .cols=3,
         // xpos and ypos
         .xpos=hpdftbl_cm2dpi(1), .ypos=hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM-2),
         // width and height
         .width=hpdftbl_cm2dpi(15), .height=0,
         // Content and label callback
         .content_cb=cb_content, .label_cb=cb_label,
// Style and table post creation callback
         .style_cb=NULL, .post_cb=NULL,
         // Pointer to optional cell specifications
         .cell_spec=NULL
void
create_table_ex13_1(HPDF_Doc pdf_doc, HPDF_Page pdf_page) {
   hpdftbl_stroke_from_data(pdf_doc, pdf_page, &tbl_spec, NULL);
^{\prime\prime} // Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
    // Setup the basic PDF document
     *pdf_doc = HPDF_New(error_handler, NULL);
     *pdf_page = HPDF_AddPage(*pdf_doc);
    HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
    if (addgrid) {
         hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file)) {
      fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int.
main(int argc, char **argv) {
```

```
HPDF_Doc pdf_doc;
HPDF_Page pdf_page;
if (setjmp(env)) {
          HPDF_Free(pdf_doc);
          return EXIT_FAILURE;
    }
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
    create_table_ex13_1(pdf_doc, pdf_page);
    stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
}
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# 15.13 tut\_ex13\_2.c

Defining a table with a data structure for table and cells.

```
/* tut_ex13_2 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <alloca.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <unistd.h>
#endif
#include <hpdf.h>
#include <math.h>
#include <setjmp.h>
#include <time.h>
#if !(defined _WIN32 || defined __WIN32__)
#include <sys/utsname.h>
#endif
// This include should always be used
\# include \ ".../src/hpdftbl.h" // The output after running the program will be written to this file
#ifdef _WIN32
#define OUTPUT_FILE "tut_ex13_2.pdf"
#else
#define OUTPUT_FILE "/tmp/tut_ex13_2.pdf"
#endif
#define TRUE 1
#define FALSE 0
// For simulated exception handling
jmp_buf env;
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions \mbox{\tt\#pragma} GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#pragma GCC diagnostic ignored "-Wformat-nonliteral"
#endif
// A standard hpdf error handler which also translates the hpdf error code to a
// human readable string
hpdftbl_hpdf_get_errstr(error_no), (unsigned int)error_no, (int)detail_no);
    longjmp(env, 1);
//static char *
//cb_date(void *tag, size_t r, size_t c) {
     static char buf[64];
      time_t t = time(NULL);
      ctime_r(&t, buf);
      return buf;
//}
static char *
cb_content(void *tag, size_t r, size_t c) {
    static char *cell_content[] =
             {"Mark Ericsen",
              "12 Sep 2021",
              "123 Downer Mews",
              "London",
              "NW2 HB3",
              "mark.p.ericsen@myfinemail.com",
              "+44734 354 184 56",
              "+44771 938 137 11"};
    if( 0==r && 0==c) return cell_content[0];
    else if (0==r && 3==c) return cell_content[1];
```

15.13 tut\_ex13\_2.c 167

```
else if (1==r && 0==c) return cell_content[2];
    else if (2==r && 0==c) return cell_content[3];
    else if (2==r && 3==c) return cell_content[4];
    else if (3==r && 0==c) return cell_content[5];
    else if (4==r && 0==c) return cell_content[6];
    else if (4==r && 2==c) return cell_content[7];
    else return NULL;
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
hpdftbl_cell_spec_t cell_specs[] = {
         {.row=0, .col=0, .rowspan=1, .colspan=3, .label="Name:",
                 .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=0, .col=3, .rowspan=1, .colspan=1,
    .label="Date:",
                  .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL),
         {.row=1, .col=0, .rowspan=1, .colspan=4,
                  .label="Address:",
                  .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL),
         {.row=2, .col=3, .rowspan=1, .colspan=1, .label="Zip:",
                  .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=4, .col=0, .rowspan=1, .colspan=2,
    .label="Workphone:",
                  .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
         {.row=4, .col=2, .rowspan=1, .colspan=2,
                  .label="Mobile:",
                  .content_cb=NULL, .label_cb=NULL, .style_cb=NULL, .canvas_cb=NULL},
        HPDFTBL END CELLSPECS
hpdftbl_spec_t tbl_spec = {
         // Title and header flag
         .title=NULL, .use_header=FALSE,
         // Label and labelgrid flags
         .use_labels=TRUE, .use_labelgrid=TRUE,
         // Row and columns
         .rows=5, .cols=4,
         // xpos and ypos
         .xpos=hpdftbl_cm2dpi(1), .ypos=hpdftbl_cm2dpi(A4PAGE_HEIGHT_CM-2),
         // width and height
         .width=hpdftbl_cm2dpi(15), .height=0,
// Content and label callback
         .content_cb=cb_content, .label_cb=0,
// Style and table post creation callback
         .style_cb=NULL, .post_cb=NULL,
         // Pointer to optional cell specifications
         .cell_spec=cell_specs
};
void
create_table_ex13_2(HPDF_Doc pdf_doc, HPDF_Page pdf_page)
   hpdftbl_stroke_from_data(pdf_doc, pdf_page, &tbl_spec, NULL);
^{\prime} // Setup a new PDF document with one page
void
setup_hpdf(HPDF_Doc* pdf_doc, HPDF_Page* pdf_page, _Bool addgrid) {
    // Setup the basic PDF document
     *pdf_doc = HPDF_New(error_handler, NULL);
    *pdf_page = HPDF_AddPage(*pdf_doc);
    HPDF_SetCompressionMode(*pdf_doc, HPDF_COMP_ALL);
HPDF_Page_SetSize(*pdf_page, HPDF_PAGE_SIZE_A4, HPDF_PAGE_PORTRAIT);
    if (addgrid) {
        hpdftbl_stroke_grid(*pdf_doc, *pdf_page);
void
stroke_pdfdoc(HPDF_Doc pdf_doc, char *file) {
   printf("Sending to file \"%s\" ...\n", file);
   if (HPDF_OK != HPDF_SaveToFile(pdf_doc, file))
        fprintf(stderr, "ERROR: Cannot save to file!");
    HPDF_Free (pdf_doc);
    printf("Done.\n");
#ifndef _MSC_VER
// Silent gcc about unused "arg" in the callback and error functions
#pragma GCC diagnostic push
#pragma GCC diagnostic ignored "-Wunused-parameter"
#endif
int
```

```
main(int argc, char **argv) {
    HPDF_Doc pdf_doc;
    HPDF_Page pdf_page;
    if (setjmp(env)) {
        HPDF_Free(pdf_doc);
        return EXIT_FAILURE;
    }
    setup_hpdf(&pdf_doc, &pdf_page, FALSE);
    create_table_ex13_2(pdf_doc, pdf_page);
    stroke_pdfdoc(pdf_doc, OUTPUT_FILE);
    return EXIT_SUCCESS;
}
#ifndef _MSC_VER
#pragma GCC diagnostic pop
#endif
```

# Index

```
/Users/ljp/Devel/hpdf_table/src/config.h, 63
                                                          content cb
/Users/ljp/Devel/hpdf_table/src/hpdftbl.c, 64
                                                               hpdftbl, 45
/Users/lip/Devel/hpdf table/src/hpdftbl.h, 94, 135
                                                               hpdftbl cell, 50
/Users/ljp/Devel/hpdf table/src/hpdftbl errstr.c, 140
                                                               hpdftbl cell spec, 52
/Users/ljp/Devel/hpdf_table/src/hpdftbl_grid.c, 141
                                                               hpdftbl_spec, 55
/Users/ljp/Devel/hpdf_table/src/hpdftbl_widget.c, 142
                                                          content_style
                                                               hpdftbl, 46
A3PAGE_HEIGHT_CM
                                                               hpdftbl cell, 50
     hpdftbl.h, 99
                                                               hpdftbl_theme, 58
A3PAGE WIDTH CM
                                                          content style cb
     hpdftbl.h, 99
                                                               hpdftbl, 46
A4PAGE HEIGHT CM
     hpdftbl.h, 99
                                                          DASH1
A4PAGE WIDTH CM
                                                               hpdftbl.h, 105
     hpdftbl.h, 99
                                                          DASH2
                                                               hpdftbl.h, 105
background
                                                          DASH3
     text_style, 61
                                                               hpdftbl.h, 105
border_style, 43
                                                          dash_ptn
     color, 43
                                                               line_dash_style, 60
     line_style, 43
                                                          DASHDOT
     width, 43
                                                               hpdftbl.h, 105
                                                          delta_x
canvas cb
                                                               hpdftbl_cell, 50
     hpdftbl, 45
                                                          delta y
     hpdftbl cell, 49
                                                               hpdftbl_cell, 50
     hpdftbl cell spec, 52
                                                          DOT1
cell spec
                                                               hpdftbl.h, 105
     hpdftbl_spec, 55
                                                          DOT2
cells
                                                               hpdftbl.h, 105
     hpdftbl, 45
                                                          DOT3
CENTER
                                                               hpdftbl.h, 105
     hpdftbl.h, 106
col
                                                          errcode
     hpdftbl_cell_spec, 52
                                                               hpdftbl errcode entry, 54
col_width_percent
                                                          errstr
     hpdftbl, 45
                                                               hpdftbl_errcode_entry, 54
color
     border_style, 43
                                                          font
     text_style, 61
                                                               text_style, 61
COLOR_DARK_RED
                                                          fsize
     hpdftbl.h, 100
                                                               text style, 62
cols
                                                          halign
     hpdftbl, 45
                                                               text_style, 62
     hpdftbl_spec, 55
                                                          header_style
colspan
                                                               hpdftbl, 46
     hpdftbl_cell, 49
                                                               hpdftbl_theme, 58
     hpdftbl cell spec, 52
                                                          height
content
                                                               hpdftbl, 46
     hpdftbl cell, 49
```

hpdftbl_cell, 50	hpdftbl_set_cell_canvas_cb, 75
hpdftbl_spec, 56	hpdftbl_set_cell_content_cb, 76
hpdf_border_style_t	hpdftbl_set_cell_content_style, 76
hpdftbl.h, 102	hpdftbl_set_cell_content_style_cb, 77
HPDF_COLOR_FROMRGB	hpdftbl_set_cell_label_cb, 78
hpdftbl.h, 100	hpdftbl_set_cellspan, 78
HPDF_FF_TIMES	hpdftbl_set_col_content_style, 79
hpdftbl.h, 100	hpdftbl_set_colwidth_percent, 80
HPDF_RoundedCornerRectangle	hpdftbl_set_content, 80
hpdftbl.c, 67	hpdftbl_set_content_cb, 81
hpdftbl.h, 106	hpdftbl_set_content_style, 81
hpdf_text_style_t	hpdftbl_set_content_style_cb, 82
hpdftbl.h, 102	hpdftbl_set_errhandler, 83
hpdftbl, 44	hpdftbl_set_header_halign, 83
canvas_cb, 45	hpdftbl_set_header_style, 84
cells, 45	hpdftbl_set_inner_border, 84
col_width_percent, 45	hpdftbl_set_label_cb, 85
cols, 45	hpdftbl_set_label_style, 85
content_cb, 45	hpdftbl_set_labels, 86
content_style, 46	hpdftbl_set_line_dash, 86
content_style_cb, 46	hpdftbl_set_outer_border, 87
header_style, 46	hpdftbl_set_row_content_style, 87
height, 46	hpdftbl_set_tag, 88
inner_border, 46	hpdftbl_set_text_encoding, 89
label_cb, 46	hpdftbl_set_title, 89
label_style, 46	hpdftbl_set_title_halign, 89
outer_border, 47	hpdftbl_set_title_style, 90
pdf_doc, 47	hpdftbl_stroke, 91
pdf_page, 47	hpdftbl_stroke_from_data, 91
posx, 47	hpdftbl_use_header, 92
posy, 47	hpdftbl_use_labelgrid, 93
rows, 47	hpdftbl_use_labels, 93
tag, 47	hpdftbl.h
title_style, 48	A3PAGE_HEIGHT_CM, 99
title_txt, 48	A3PAGE_WIDTH_CM, 99
use_cell_labels, 48	A4PAGE_HEIGHT_CM, 99
use_header_row, 48	A4PAGE_WIDTH_CM, 99
use_label_grid_style, 48	CENTER, 106
width, 48	COLOR_DARK_RED, 100
hpdftbl.c	DASH1, 105
HPDF_RoundedCornerRectangle, 67	DASH2, 105
hpdftbl_apply_theme, 67	DASH3, 105
hpdftbl_clear_spanning, 68	
	DASHDOT, 105
hpdftbl_create, 68	DASHDOT, 105 DOT1, 105
hpdftbl_create_title, 69	DASHDOT, 105 DOT1, 105 DOT2, 105
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71 hpdftbl_get_errstr, 72	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102 hpdftbl_apply_theme, 106
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71 hpdftbl_get_errstr, 72 hpdftbl_get_last_auto_height, 72	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102 hpdftbl_apply_theme, 106 hpdftbl_callback_t, 102
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71 hpdftbl_get_errstr, 72 hpdftbl_get_last_auto_height, 72 hpdftbl_get_last_errcode, 73	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102 hpdftbl_apply_theme, 106 hpdftbl_callback_t, 102 hpdftbl_canvas_callback_t, 102
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71 hpdftbl_get_errstr, 72 hpdftbl_get_last_auto_height, 72 hpdftbl_get_last_errcode, 73 hpdftbl_set_anchor_top_left, 73	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102 hpdftbl_apply_theme, 106 hpdftbl_callback_t, 102 hpdftbl_canvas_callback_t, 102 hpdftbl_cell_spec_t, 103
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71 hpdftbl_get_last_auto_height, 72 hpdftbl_get_last_errcode, 73 hpdftbl_set_anchor_top_left, 73 hpdftbl_set_background, 74	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102 hpdftbl_apply_theme, 106 hpdftbl_callback_t, 102 hpdftbl_callback_t, 102 hpdftbl_cell_spec_t, 103 hpdftbl_cell_spec_t, 103 hpdftbl_cell_t, 103
hpdftbl_create_title, 69 hpdftbl_default_table_error_handler, 69 hpdftbl_destroy, 70 hpdftbl_destroy_theme, 70 hpdftbl_encoding_text_out, 71 hpdftbl_get_anchor_top_left, 71 hpdftbl_get_default_theme, 71 hpdftbl_get_errstr, 72 hpdftbl_get_last_auto_height, 72 hpdftbl_get_last_errcode, 73 hpdftbl_set_anchor_top_left, 73	DASHDOT, 105 DOT1, 105 DOT2, 105 DOT3, 105 hpdf_border_style_t, 102 HPDF_COLOR_FROMRGB, 100 HPDF_FF_TIMES, 100 HPDF_RoundedCornerRectangle, 106 hpdf_text_style_t, 102 hpdftbl_apply_theme, 106 hpdftbl_callback_t, 102 hpdftbl_canvas_callback_t, 102 hpdftbl_cell_spec_t, 103

hpdftbl_content_callback_t, 103	hpdftbl_use_labelgrid, 131
hpdftbl_content_style_callback_t, 103	hpdftbl_use_labels, 132
hpdftbl_create, 107	hpdftbl_widget_hbar, 132
hpdftbl_create_title, 108	hpdftbl_widget_segment_hbar, 133
hpdftbl dash style, 105	hpdftbl_widget_slide_button, 134
hpdftbl_default_table_error_handler, 108	hpdftbl widget strength meter, 134
HPDFTBL_DEFAULT_TARGET_ENCODING, 101	LEFT, 106
hpdftbl_destroy, 109	LEGALPAGE_HEIGHT_CM, 101
• — •	
hpdftbl_destroy_theme, 109	LEGALPAGE_WIDTH_CM, 101
hpdftbl_encoding_text_out, 109	LETTERPAGE_HEIGHT_CM, 101
HPDFTBL_END_CELLSPECS, 101	LETTERRPAGE_WIDTH_CM, 101
hpdftbl_error_handler_t, 104	MIN_CALCULATED_PERCENT_CELL_WIDTH,
hpdftbl_get_anchor_top_left, 110	102
hpdftbl_get_default_theme, 110	RIGHT, 106
hpdftbl_get_errstr, 110	SOLID, 105
hpdftbl_get_last_auto_height, 111	hpdftbl_apply_theme
hpdftbl_get_last_errcode, 111	hpdftbl.c, 67
hpdftbl_hpdf_get_errstr, 112	hpdftbl.h, 106
hpdftbl_set_anchor_top_left, 112	hpdftbl_callback_t
hpdftbl_set_background, 113	hpdftbl.h, 102
hpdftbl_set_canvas_cb, 113	hpdftbl_canvas_callback_t
hpdftbl_set_cell, 114	hpdftbl.h, 102
hpdftbl_set_cell_canvas_cb, 114	hpdftbl_cell, 49
hpdftbl_set_cell_content_cb, 115	canvas_cb, 49
hpdftbl_set_cell_content_style, 115	colspan, 49
hpdftbl_set_cell_content_style_cb, 116	content, 49
hpdftbl_set_cell_label_cb, 117	content_cb, 50
hpdftbl_set_cellspan, 117	content_style, 50
hpdftbl_set_col_content_style, 118	delta_x, 50
hpdftbl_set_colwidth_percent, 119	delta_y, 50
hpdftbl_set_content, 119	height, 50
hpdftbl_set_content_cb, 120	label, 50
hpdftbl_set_content_style, 120	label_cb, 50
hpdftbl_set_content_style_cb, 121	parent_cell, 50
hpdftbl_set_errhandler, 121	rowspan, 51
hpdftbl_set_header_halign, 122	style_cb, 51
hpdftbl_set_header_style, 122	textwidth, 51
hpdftbl_set_inner_border, 123	width, 51
hpdftbl_set_label_cb, 123	hpdftbl_cell_spec, 51
hpdftbl_set_label_style, 124	canvas_cb, 52
hpdftbl_set_labels, 124	col, <u>52</u>
hpdftbl_set_outer_border, 125	colspan, 52
hpdftbl_set_row_content_style, 125	content_cb, 52
hpdftbl_set_tag, 126	label, 53
hpdftbl_set_text_encoding, 126	label_cb, 53
hpdftbl set title, 127	row, 53
hpdftbl_set_title_halign, 127	rowspan, 53
hpdftbl set title style, 128	style_cb, 53
hpdftbl_spec_t, 104	hpdftbl_cell_spec_t
hpdftbl_stroke, 128	hpdftbl.h, 103
hpdftbl_stroke_from_data, 129	hpdftbl_cell_t
hpdftbl_stroke_grid, 130	hpdftbl.h, 103
hpdftbl_t, 104	hpdftbl_clear_spanning
hpdftbl_table_widget_letter_buttons, 130	hpdftbl.c, 68
hpdftbl_text_align, 105	hpdftbl.h, 107
hpdftbl_text_align_t, 104	hpdftbl_cm2dpi
hpdftbl_theme_t, 105	hpdftbl.h, 100
hpdftbl use header, 131	hpdftbl content callback t
· · · · · · · · · · · · · · · · · · ·	

hpdftbl.h, 103	hpdftbl.c, 74
hpdftbl_content_style_callback_t	hpdftbl.h, 113
hpdftbl.h, 103	hpdftbl_set_canvas_cb
hpdftbl_create	hpdftbl.c, 74
hpdftbl.c, 68	hpdftbl.h, 113
hpdftbl.h, 107	hpdftbl_set_cell
hpdftbl_create_title	hpdftbl.c, 75
hpdftbl.c, 69	hpdftbl.h, 114
hpdftbl.h, 108	hpdftbl_set_cell_canvas_cb
hpdftbl_dash_style	hpdftbl.c, 75
hpdftbl.h, 105	hpdftbl.h, 114
hpdftbl_default_table_error_handler	hpdftbl_set_cell_content_cb
hpdftbl.c, 69	hpdftbl.c, 76
hpdftbl.h, 108	hpdftbl.h, 115
HPDFTBL_DEFAULT_TARGET_ENCODING	hpdftbl_set_cell_content_style
hpdftbl.h, 101	hpdftbl.c, 76
hpdftbl_destroy	hpdftbl.h, 115
hpdftbl.c, 70	hpdftbl_set_cell_content_style_cb
hpdftbl.h, 109	hpdftbl.c, 77
hpdftbl_destroy_theme	hpdftbl.h, 116
hpdftbl.c, 70	hpdftbl_set_cell_label_cb
hpdftbl.h, 109	hpdftbl.c, 78
hpdftbl_encoding_text_out	hpdftbl.h, 117
hpdftbl.c, 71	hpdftbl_set_cellspan
hpdftbl.h, 109	hpdftbl.c, 78
HPDFTBL_END_CELLSPECS	hpdftbl.h, 117
hpdftbl.h, 101	hpdftbl_set_col_content_style
hpdftbl_errcode_entry, 54	hpdftbl.c, 79
errcode, 54	hpdftbl.h, 118
errstr, 54	hpdftbl_set_colwidth_percent
hpdftbl_error_handler_t	hpdftbl.c, 80
hpdftbl.h, 104	hpdftbl.h, 119
hpdftbl_errstr.c	hpdftbl_set_content
hpdftbl_hpdf_get_errstr, 141	hpdftbl.c, 80
hpdftbl_get_anchor_top_left	hpdftbl.h, 119
hpdftbl.c, 71	hpdftbl_set_content_cb
hpdftbl.h, 110	hpdftbl.c, 81
hpdftbl_get_default_theme	hpdftbl.h, 120
hpdftbl.c, 71	hpdftbl_set_content_style
hpdftbl.h, 110	hpdftbl.c, 81
hpdftbl_get_errstr	hpdftbl.h, 120
hpdftbl.c, 72	hpdftbl_set_content_style_cb
hpdftbl.h, 110	hpdftbl.c, 82
hpdftbl_get_last_auto_height	hpdftbl.h, 121
hpdftbl.c, 72	hpdftbl_set_errhandler
hpdftbl.h, 111	hpdftbl.c, 83
hpdftbl_get_last_errcode	hpdftbl.h, 121
hpdftbl.c, 73	hpdftbl_set_header_halign
hpdftbl.h, 111	hpdftbl.c, 83
hpdftbl_grid.c	hpdftbl.h, 122
hpdftbl_stroke_grid, 142	hpdftbl_set_header_style
hpdftbl_hpdf_get_errstr	hpdftbl.c, 84
hpdftbl.h, 112	hpdftbl.h, 122
hpdftbl_errstr.c, 141	hpdftbl_set_inner_border
hpdftbl_set_anchor_top_left	hpdftbl.c, 84
hpdftbl.c, 73	hpdftbl.h, 123
hpdftbl.h, 112	hpdftbl_set_label_cb
hpdftbl_set_background	hpdftbl.c, 85

hpdftbl.h, 123	hpdftbl.h, 104
hpdftbl_set_label_style	hpdftbl_table_widget_letter_buttons
hpdftbl.c, 85	hpdftbl.h, 130
•	•
hpdftbl.h, 124	hpdftbl_widget.c, 143
hpdftbl_set_labels	hpdftbl_text_align
hpdftbl.c, 86	hpdftbl.h, 105
hpdftbl.h, 124	hpdftbl_text_align_t
hpdftbl_set_line_dash	hpdftbl.h, 104
hpdftbl.c, 86	hpdftbl_theme, 58
hpdftbl_set_outer_border	content_style, 58
hpdftbl.c, 87	header_style, 58
hpdftbl.h, 125	inner_border, 59
hpdftbl_set_row_content_style	label_style, 59
hpdftbl.c, 87	outer_border, 59
hpdftbl.h, 125	title_style, 59
hpdftbl_set_tag	use_header_row, 59
hpdftbl.c, 88	use_label_grid_style, 59
hpdftbl.h, 126	use_labels, 59
hpdftbl_set_text_encoding	hpdftbl_theme_t
hpdftbl.c, 89	hpdftbl.h, 105
hpdftbl.h, 126	hpdftbl_use_header
hpdftbl_set_title	hpdftbl.c, 92
• — —	•
hpdftbl.c, 89	hpdftbl.h, 131
hpdftbl.h, 127	hpdftbl_use_labelgrid
hpdftbl_set_title_halign	hpdftbl.c, 93
hpdftbl.c, 89	hpdftbl.h, 131
hpdftbl.h, 127	hpdftbl_use_labels
hpdftbl_set_title_style	hpdftbl.c, 93
hpdftbl.c, 90	hpdftbl.h, 132
hpdftbl.h, 128	hpdftbl_widget.c
hpdftbl_spec, 54	hpdftbl_table_widget_letter_buttons, 143
cell_spec, 55	hpdftbl_widget_hbar, 144
cols, 55	hpdftbl_widget_segment_hbar, 144
content_cb, 55	hpdftbl_widget_slide_button, 145
height, 56	hpdftbl_widget_strength_meter, 146
label cb, 56	hpdftbl_widget_hbar
post_cb, 56	hpdftbl.h, 132
rows, 56	hpdftbl_widget.c, 144
style_cb, 56	hpdftbl_widget_segment_hbar
title, 56	hpdftbl.h, 133
use_header, 57	hpdftbl_widget.c, 144
use_labelgrid, 57	hpdftbl_widget_slide_button
use_labels, 57	hpdftbl.h, 134
	•
width, 57	hpdftbl_widget.c, 145
xpos, 57	hpdftbl_widget_strength_meter
ypos, 57	hpdftbl.h, 134
hpdftbl_spec_t	hpdftbl_widget.c, 146
hpdftbl.h, 104	inner berder
hpdftbl_stroke	inner_border
hpdftbl.c, 91	hpdftbl, 46
hpdftbl.h, 128	hpdftbl_theme, 59
hpdftbl_stroke_from_data	l-b-l
hpdftbl.c, 91	label
hpdftbl.h, 129	hpdftbl_cell, 50
hpdftbl_stroke_grid	hpdftbl_cell_spec, 53
hpdftbl.h, 130	label_cb
hpdftbl_grid.c, 142	hpdftbl, 46
hpdftbl_t	hpdftbl_cell, 50
· =	hpdftbl_cell_spec, 53

hpdftbl_spec, 56	tag
label_style	hpdftbl, 47
hpdftbl, 46	text_style, 61
hpdftbl_theme, 59	background, 61
LEFT	color, 61
hpdftbl.h, 106	font, 61
LEGALPAGE_HEIGHT_CM	fsize, 62
hpdftbl.h, 101	halign, 62
LEGALPAGE_WIDTH_CM hpdftbl.h, 101	textwidth
LETTERRPAGE_HEIGHT_CM	hpdftbl_cell, 51 title
hpdftbl.h, 101	hpdftbl_spec, 56
LETTERRPAGE_WIDTH_CM	title_style
hpdftbl.h, 101	hpdftbl, 48
line_dash_style, 60	hpdftbl_theme, 59
dash_ptn, 60	title_txt
num, 60	hpdftbl, 48
line_style	
border_style, 43	use_cell_labels
ANN CALCULATED DEDOENT OF L. MIDTH	hpdftbl, 48
MIN_CALCULATED_PERCENT_CELL_WIDTH	use_header
hpdftbl.h, 102	hpdftbl_spec, 57
num	use_header_row hpdftbl, 48
line_dash_style, 60	hpdftbl_theme, 59
<b>,</b> ,	use_label_grid_style
outer_border	hpdftbl, 48
hpdftbl, 47	hpdftbl_theme, 59
hpdftbl_theme, 59	use_labelgrid
parent cell	hpdftbl_spec, 57
hpdftbl_cell, 50	use_labels
pdf_doc	hpdftbl_spec, 57
hpdftbl, 47	hpdftbl_theme, 59
pdf_page	
hpdftbl, 47	width
post_cb	border_style, 43
hpdftbl_spec, 56	hpdftbl, 48
posx	hpdftbl_cell, 51 hpdftbl_spec, 57
hpdftbl, 47	ripulibi_spec, 57
posy	xpos
hpdftbl, 47	hpdftbl_spec, 57
RIGHT	
hpdftbl.h, 106	ypos
row	hpdftbl_spec, 57
hpdftbl_cell_spec, 53	
rows	
hpdftbl, 47	
hpdftbl_spec, 56	
rowspan	
hpdftbl_cell, 51	
hpdftbl_cell_spec, 53	
COLID	
SOLID	
hpdftbl.h, 105	
style_cb hpdftbl_cell, 51	
hpdftbl_cell_spec, 53	
pa.toi_00ii_0p00, 00	