Installation instructions for xkl on Windows

Prerequisites

The installation of xkl on Windows requires the Cygwin software package to be installed on Windows. Installation instructions can be found at https://x.cygwin.com/docs/ug/cygwin-x-ug.pdf; during the installation procedure select the lynx package for installation.

After the installation procedure is complete, open a Cygwin terminal from your Desktop or Start Menu. From the terminal:

• install the apt-cyg utility using lynx, by running the commands:

```
lynx -source rawgit.com/transcode-open/apt-cyg/master/apt-cyg > apt-
cyg
install apt-cyg /bin
```

(detailed installation instructions are available at https://github.com/transcode-open/apt-cyg)

use apt-cyg to install the packages required by xkl by running the following command: apt-cyg install wget cygwin-devel gcc-core libXmu-devel libXmu6 libXmuu1 libXt-devel libXt6 make makedepend motif libXm-devel xorgserver xinit libguile2.2 1 libgc1 libltd17 libmpc3 libis123 libX11devel xorgproto binutils libSM-devel libICE-devel libXpm-devel mingw64-x86 64-runtime libXm4 xterm libfontconfig1 libXpm4 libXineramal libXft2 libXaw7 libICE6 libSM6 libXrender1 libjpeg8 sox libsox3 libFLAC8 libgsm1 libid3tag0 libmad0 libogg0 libmp3lame0 libopus0 libopusfile0 libsndfile1 libtwolame0 libvorbis0 libvorbisenc2 libvorbisfile3 libwavpack1 libgomp1 libguile3.0 1-3.0.8-1 libcrypt2-4.4.4-1 libunistring2-0.9.10-1 libX11 6-1.8.1-1 libxcb1-1.15-1 libXau6-1.0.11-1 libXdmcp6-1.1.4-1 libxcb-xfixes0-1.15-1 libxcb-util1-0.4.0-1 libxcb-image0-0.4.1-1 libxcb-icccm4-0.4.2-1 libxcb-ewmh2-0.4.2-1 libxcb-composite0-1.15-1 libtirpc3-1.3.3-1 libpixman1 0-0.42.2-1 libXfont2 2-2.0.6-1 libfontenc1-1.1.7-1 libfreetype6-2.12.1-1 libgssapi krb5 2-1.15.2-2 libxcb-shm0-1.15-1 libbrotlidec1-1.0.9-2 libpng16- $\overline{1}$.6.3 $\overline{7}$ -1 libk5crypto3-1.15.2-2 libkrb5 3-1.15.2-2 libkrb5support0-1.15.2-2 libcom err2-1.44.5-1 libbrotlicommon1-1.0.9-2

• run again the Cygwin installer, select all pending libraries and install them.

Installation procedure

- Copy the source folder *xkl_windows* to *C:\cygwin64\home\<username>* (where <username> is the windows user name used during the Cygwin installation).
- Open a Cygwin Terminal and issue the ls command: the *xkl_windows* folder should show up in the terminal.
- Move into the folder with the command:

```
cd xkl windows
```

• Execute the following commands:

```
make clean
make
```

Running xkl

- Start the Xserver. This can be done in several ways:
 - o by selecting the Xwin Server icon in the Windows Start menu,
 - by opening a Cygwin terminal and running the commands:
 xinit -- -multiwindow
 - by running the script xserver_init_script provided along with the source code, that
 executes the same commands. Copy the file in the xkl_windows folder and run the
 command

```
./xserver init script
```

export DISPLAY=:0.0

• The above commands will open an xterm shell. In this shell move into the folder containing the xkl executable with the command:

```
cd xkl windows/xkl
```

• You can now start xkl with the command:

```
./xk1-3.2
```

but it is preferable to open it by directly providing an input .wav file (see *Notes and caveats* for the reason) by typing (e.g. for the file *heavens.wav*)

```
./xkl-3.2 heavens.wav
```

Notes and caveats

- The above procedure has been tested under Windows 11, but it should work on earlier Windows versions.
- Some of the windows are hidden at random when xkl is opened without providing an input file, and when it happens windows stay hidden even when a file is opened. However, the issue does not seem to appear when an input file is provided at launch.
- .wav files generated by most acquisition programs (e.g. Audacity) adopt MS headers, while xkl requires Klatt headers. MS .wav files can be converted by using the *ms2kl* program, that is generated during the compilation in the *xkl_windows/utils* folder. Just copy the MS .wav file (e.g. *test.wav*) in the *utils* folder, and in a Cygwin terminal type the commands

```
cd xkl_windows/utils
./ms2kl test.wav
```

that will generate in the same folder a new .wav file named *test_kl.wav* that can be opened with xkl.

- The play function uses the *sox* tool and two scripts in the *utils* subfolder. This is transparent to the user, provided that the internal folder structure under *xkl_windows* is not changed, and the application is launched in a Cygwin terminal or xterm shell from the directory *xkl_windows/xkl*.
- The record function also uses the *sox* tool and two scripts in the *utils* subfolder. When a recording is started, the user is required to provide a file name that is used to save the recorded waveform in the *xkl* folder using the Microsoft (MS) .wav format. A version of the waveform is also saved in the Klatt format with the same name extended with the suffix _kl, and automatically opened in *xkl*.