

Red Hat Ceph Storage 4

Installation Guide

Installing Red Hat Ceph Storage on Red Hat Enterprise Linux

Last Updated: 2020-07-17

Red Hat Ceph Storage 4 Installation Guide

Installing Red Hat Ceph Storage on Red Hat Enterprise Linux

Legal Notice

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document provides instructions on installing Red Hat Ceph Storage on Red Hat Enterprise Linux 8 running on AMD64 and Intel 64 architectures.

Table of Contents

CHAPTER 1. WHAT IS RED HAT CEPH STORAGE?	. 4
CHAPTER 2. REQUIREMENTS FOR INSTALLING RED HAT CEPH STORAGE	. 6
2.1. PREREQUISITES	6
2.2. REQUIREMENTS CHECKLIST FOR INSTALLING RED HAT CEPH STORAGE	6
2.3. OPERATING SYSTEM REQUIREMENTS FOR RED HAT CEPH STORAGE	7
2.4. REGISTERING RED HAT CEPH STORAGE NODES TO THE CDN AND ATTACHING SUBSCRIPTIONS	8
2.5. ENABLING THE RED HAT CEPH STORAGE REPOSITORIES	12
2.6. CONSIDERATIONS FOR USING A RAID CONTROLLER WITH OSD NODES	14
2.7. CONSIDERATIONS FOR USING NVME WITH OBJECT GATEWAY	14
2.8. VERIFYING THE NETWORK CONFIGURATION FOR RED HAT CEPH STORAGE	15
2.9. CONFIGURING A FIREWALL FOR RED HAT CEPH STORAGE	15
2.10. CREATING AN ANSIBLE USER WITH SUDO ACCESS	19
2.11. ENABLING PASSWORD-LESS SSH FOR ANSIBLE	21
2.12. CONFIGURING ANSIBLE INVENTORY LOCATION	23
CHAPTER 3. INSTALLING RED HAT CEPH STORAGE USING THE COCKPIT WEB INTERFACE	25
3.1. PREREQUISITES	25
3.2. INSTALLATION REQUIREMENTS	25
3.3. INSTALL AND CONFIGURE THE COCKPIT CEPH INSTALLER	25
3.4. COPY THE COCKPIT CEPH INSTALLER SSH KEY TO ALL NODES IN THE CLUSTER	29
3.5. LOG IN TO COCKPIT	30
3.6. COMPLETE THE ENVIRONMENT PAGE OF THE COCKPIT CEPH INSTALLER	32
3.7. COMPLETE THE HOSTS PAGE OF THE COCKPIT CEPH INSTALLER	36
3.8. COMPLETE THE VALIDATE PAGE OF THE COCKPIT CEPH INSTALLER	40
3.9. COMPLETE THE NETWORK PAGE OF THE COCKPIT CEPH INSTALLER	43
3.10. REVIEW THE INSTALLATION CONFIGURATION	46
3.11. DEPLOY THE CEPH CLUSTER	47
CHAPTER 4. INSTALLING RED HAT CEPH STORAGE USING ANSIBLE	53
4.1. PREREQUISITES	53
4.2. INSTALLING A RED HAT CEPH STORAGE CLUSTER	53
4.3. CONFIGURING OSD ANSIBLE SETTINGS FOR ALL NVME STORAGE	66
4.4. INSTALLING METADATA SERVERS	67
4.5. INSTALLING THE CEPH CLIENT ROLE	68
4.6. INSTALLING THE CEPH OBJECT GATEWAY	70
4.7. CONFIGURING MULTISITE CEPH OBJECT GATEWAYS	72
4.7.1. Prerequisites	73
4.7.2. Configuring a multisite Ceph Object Gateway with one realm	73
4.7.3. Configuring a multisite Ceph Object Gateway with multiple realms	76
4.7.4. Configuring a multisite Ceph Object Gateway with multiple realms and multiple RGW instances	82
4.8. DEPLOYING OSDS WITH DIFFERENT HARDWARE ON THE SAME HOST	88
4.9. INSTALLING THE NFS-GANESHA GATEWAY	90
4.10. UNDERSTANDING THE LIMIT OPTION	92
4.11. THE PLACEMENT GROUP AUTOSCALER	93
4.11.1. Configuring the placement group autoscaler	94
4.12. ADDITIONAL RESOURCES	95
CHAPTER 5. COLOCATION OF CONTAINERIZED CEPH DAEMONS	96
5.1. HOW COLOCATION WORKS AND ITS ADVANTAGES	96
How Colocation Works	96
5.2. SETTING DEDICATED RESOURCES FOR COLOCATED DAEMONS	98

5.3. ADDITIONAL RESOURCES	99
CHAPTER 6. UPGRADING A RED HAT CEPH STORAGE CLUSTER 6.1. SUPPORTED RED HAT CEPH STORAGE UPGRADE SCENARIOS 6.2. PREPARING FOR AN UPGRADE 6.3. UPGRADING THE STORAGE CLUSTER USING ANSIBLE 6.4. UPGRADING THE STORAGE CLUSTER USING THE COMMAND-LINE INTERFACE	100 101 102 105 111
CHAPTER 7. MANUALLY UPGRADING A RED HAT CEPH STORAGE CLUSTER AND OPERATING SYSTEM	
7.1. PREREQUISITES 7.2. MANUALLY UPGRADING CEPH MONITOR NODES AND THEIR OPERATING SYSTEMS 7.3. MANUALLY UPGRADING CEPH OSD NODES AND THEIR OPERATING SYSTEMS 7.4. MANUALLY UPGRADING CEPH OBJECT GATEWAY NODES AND THEIR OPERATING SYSTEMS 7.5. MANUALLY UPGRADING THE CEPH DASHBOARD NODE AND ITS OPERATING SYSTEM 7.6. RECOVERING FROM AN OPERATING SYSTEM UPGRADE FAILURE ON AN OSD NODE 7.7. ADDITIONAL RESOURCES	114 114 117 121 123 124 126
CHAPTER 8. WHAT TO DO NEXT?	127
APPENDIX A. TROUBLESHOOTING A.1. ANSIBLE STOPS INSTALLATION BECAUSE IT DETECTS LESS DEVICES THAN EXPECTED	128 128
APPENDIX B. USING THE COMMAND-LINE INTERFACE TO INSTALL THE CEPH SOFTWARE B.1. INSTALLING THE CEPH COMMAND LINE INTERFACE B.2. MANUALLY INSTALLING RED HAT CEPH STORAGE Monitor Bootstrapping OSD Bootstrapping B.3. MANUALLY INSTALLING CEPH MANAGER B.4. MANUALLY INSTALLING CEPH BLOCK DEVICE B.5. MANUALLY INSTALLING CEPH OBJECT GATEWAY	129 129 130 135 139 140 143
APPENDIX C. OVERRIDING CEPH DEFAULT SETTINGS	146
APPENDIX D. IMPORTING AN EXISTING CEPH CLUSTER TO ANSIBLE	147
APPENDIX E. PURGING STORAGE CLUSTERS DEPLOYED BY ANSIBLE	148
APPENDIX F. GENERAL ANSIBLE SETTINGS	150
APPENDIX G. OSD ANSIBLE SETTINGS	153

CHAPTER 1. WHAT IS RED HAT CEPH STORAGE?

Red Hat Ceph Storage is a scalable, open, software-defined storage platform that combines an enterprise-hardened version of the Ceph storage system with a Ceph management platform, deployment utilities, and support services.

Red Hat Ceph Storage is designed for cloud infrastructure and web-scale object storage. Red Hat Ceph Storage clusters consist of the following types of nodes:

Red Hat Ceph Storage Ansible administration

This type of node acts as the traditional Ceph Administration node did for previous versions of Red Hat Ceph Storage. This type of node provides the following functions:

- Centralized storage cluster management.
- The Ceph configuration files and keys.
- Optionally, local repositories for installing Ceph on nodes that cannot access the Internet for security reasons.

Ceph Monitor

Each Ceph Monitor node runs the **ceph-mon** daemon, which maintains a master copy of the storage cluster map. The storage cluster map includes the storage cluster topology. A client connecting to the Ceph storage cluster retrieves the current copy of the storage cluster map from the Ceph Monitor, which enables the client to read from and write data to the storage cluster.



IMPORTANT

The storage cluster can run with only one Ceph Monitor; however, to ensure high availability in a production storage cluster, Red Hat will only support deployments with at least three Ceph Monitor nodes. Red Hat recommends deploying a total of 5 Ceph Monitors for storage clusters exceeding 750 Ceph OSDs.

Ceph OSD

Each Ceph Object Storage Device (OSD) node runs the **ceph-osd** daemon, which interacts with logical disks attached to the node. The storage cluster stores data on these Ceph OSD nodes.

Ceph can run with very few OSD nodes, which the default is three, but production storage clusters realize better performance beginning at modest scales. For example, 50 Ceph OSDs in a storage cluster. Ideally, a Ceph storage cluster has multiple OSD nodes, allowing for the possibility to isolate failure domains by configuring the CRUSH map accordingly.

Ceph MDS

Each Ceph Metadata Server (MDS) node runs the **ceph-mds** daemon, which manages metadata related to files stored on the Ceph File System (CephFS). The Ceph MDS daemon also coordinates access to the shared storage cluster.

Ceph Object Gateway

Ceph Object Gateway node runs the **ceph-radosgw** daemon, and is an object storage interface built on top of **librados** to provide applications with a RESTful access point to the Ceph storage cluster. The Ceph Object Gateway supports two interfaces:

S3

Provides object storage functionality with an interface that is compatible with a large subset of the Amazon S3 RESTful API.

Swift


Provides object storage functionality with an interface that is compatible with a large subset of the OpenStack Swift API.

Additional Resources

- For details on the Ceph architecture, see the *Red Hat Ceph Storage Architecture Guide*.
- For the minimum hardware recommendations, see the *Red Hat Ceph Storage Hardware Selection Guide*.

CHAPTER 2. REQUIREMENTS FOR INSTALLING RED HAT CEPH STORAGE

Figure 2.1. Prerequisite Workflow



Before installing Red Hat Ceph Storage, review the following requirements and prepare each Monitor, OSD, Metadata Server, and client nodes accordingly.

2.1. PREREQUISITES

• Verify the hardware meets the minimum requirements for Red Hat Ceph Storage 4.

2.2. REQUIREMENTS CHECKLIST FOR INSTALLING RED HAT CEPH STORAGE

Task	Required	Section	Recommendation
Verifying the operating system version	Yes	Section 2.3, "Operating system requirements for Red Hat Ceph Storage"	
Registering Ceph nodes	Yes	Section 2.4, "Registering Red Hat Ceph Storage nodes to the CDN and attaching subscriptions"	
Enabling Ceph software repositories	Yes	Section 2.5, "Enabling the Red Hat Ceph Storage repositories"	
Using a RAID controller with OSD nodes	No	Section 2.6, "Considerations for using a RAID controller with OSD nodes"	Enabling write-back caches on a RAID controller might result in increased small I/O write throughput for OSD nodes.

Task	Required	Section	Recommendation
Configuring the network	Yes	Section 2.8, "Verifying the network configuration for Red Hat Ceph Storage"	At minimum, a public network is required. However, a private network for cluster communication is recommended.
Configuring a firewall	No	Section 2.9, "Configuring a firewall for Red Hat Ceph Storage"	A firewall can increase the level of trust for a network.
Creating an Ansible user	Yes	Section 2.10, "Creating an Ansible user with sudo access"	Creating the Ansible user is required on all Ceph nodes.
Enabling password- less SSH	Yes	Section 2.11, "Enabling password-less SSH for Ansible"	Required for Ansible.



NOTE

By default, **ceph-ansible** installs NTP/chronyd as a requirement. If NTP/chronyd is customized, refer to *Configuring the Network Time Protocol for Red Hat Ceph Storage* in Manually Installing Red Hat Ceph Storage section to understand how NTP/chronyd must be configured to function properly with Ceph.

2.3. OPERATING SYSTEM REQUIREMENTS FOR RED HAT CEPH STORAGE

Red Hat Ceph Storage 4 is supported on Red Hat Enterprise Linux 7 or Red Hat Enterprise Linux 8. If using Red Hat Enterprise Linux 7, use 7.7 or higher. If using Red Hat Enterprise Linux 8, use 8.1 or higher.

Red Hat Ceph Storage 4 is supported on RPM-based deployments or container-based deployments.



IMPORTANT

Deploying Red Hat Ceph Storage 4 in containers on Red Hat Enterprise Linux 7.7 will deploy Red Hat Ceph Storage 4 on a Red Hat Enterprise Linux 8 container image.

Use the same operating system version, architecture, and deployment type across all nodes. For example, do not use a mixture of nodes with both AMD64 and Intel 64 architectures, a mixture of nodes with both Red Hat Enterprise Linux 7 and Red Hat Enterprise Linux 8 operating systems, or a mixture of nodes with both RPM-based deployments and container-based deployments.



IMPORTANT

Red Hat does not support clusters with heterogeneous architectures, operating system versions, or deployment types.

SELinux

By default, SELinux is set to **Enforcing** mode and the **ceph-selinux** packages are installed. For additional information on SELinux please see the *Data Security and Hardening Guide*, *Red Hat Enterprise Linux 7 SELinux User's and Administrator's Guide*, and *Red Hat Enterprise Linux 8 Using SELinux Guide*.

Additional Resources

- The documentation set for Red Hat Enterprise Linux 8 is available at https://access.redhat.com/documentation/en-us/red_hat_enterprise_linux/8/
- The documentation set for Red Hat Enterprise Linux 7 is available at https://access.redhat.com/documentation/en-us/red_hat_enterprise_linux/7/.

Return to requirements checklist

2.4. REGISTERING RED HAT CEPH STORAGE NODES TO THE CDN AND ATTACHING SUBSCRIPTIONS

Register each Red Hat Ceph Storage node to the Content Delivery Network (CDN) and attach the appropriate subscription so that the node has access to software repositories. Each Red Hat Ceph Storage node must be able to access the full Red Hat Enterprise Linux 8 base content and the extras repository content. Perform the following steps on all bare-metal and container nodes in the storage cluster, unless otherwise noted.



NOTE

For bare-metal Red Hat Ceph Storage nodes that cannot access the Internet during the installation, provide the software content by using the Red Hat Satellite server. Alternatively, mount a local Red Hat Enterprise Linux 8 Server ISO image and point the Red Hat Ceph Storage nodes to the ISO image. For additional details, contact Red Hat Support.

For more information on registering Ceph nodes with the Red Hat Satellite server, see the How to Register Ceph with Satellite 6 and How to Register Ceph with Satellite 5 articles on the Red Hat Customer Portal.

Prerequisites

- A valid Red Hat subscription.
- Red Hat Ceph Storage nodes must be able to connect to the Internet.
- Root-level access to the Red Hat Ceph Storage nodes.

Procedure

- For container deployments only, when the Red Hat Ceph Storage nodes do NOT have access
 to the Internet during deployment. You must follow these steps first on a node with Internet
 access:
 - a. Start a local Docker registry:

Red Hat Enterprise Linux 7

docker run -d -p 5000:5000 --restart=always --name registry registry:2

Red Hat Enterprise Linux 8

podman run -d -p 5000:5000 --restart=always --name registry registry:2

b. Verify **registry.redhat.io** is in the container registry search path. Open for editing the **/etc/containers/registries.conf** file:

[registries.search]
registries = ['registry.access.redhat.com', 'registry.fedoraproject.org',
'registry.centos.org', 'docker.io']

If **registry.redhat.io** is not included in the file, add it:

[registries.search]
registries = ['registry.redhat.io', 'registry.access.redhat.com', 'registry.fedoraproject.org', 'registry.centos.org', 'docker.io']

c. Pull the Red Hat Ceph Storage 4 image, Prometheus image, and Dashboard image from the Red Hat Customer Portal:

Red Hat Enterprise Linux 7

- # docker pull registry.redhat.io/rhceph/rhceph-4-rhel8
- # docker pull registry.redhat.io/openshift4/ose-prometheus-node-exporter:v4.1
- # docker pull registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8
- # docker pull registry.redhat.io/openshift4/ose-prometheus:4.1
- # docker pull registry.redhat.io/openshift4/ose-prometheus-alertmanager:4.1

Red Hat Enterprise Linux 8

- # podman pull registry.redhat.io/rhceph/rhceph-4-rhel8
- # podman pull registry.redhat.io/openshift4/ose-prometheus-node-exporter:v4.1
- # podman pull registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8
- # podman pull registry.redhat.io/openshift4/ose-prometheus:4.1
- # podman pull registry.redhat.io/openshift4/ose-prometheus-alertmanager:4.1



NOTE

Red Hat Enterprise Linux 7 and 8 both use the same container image, based on Red Hat Enterprise Linux 8.

d. Tag the image:

Red Hat Enterprise Linux 7

docker tag registry.redhat.io/rhceph/rhceph-4-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

docker tag registry.redhat.io/openshift4/ose-prometheus-node-exporter:v4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

docker tag registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

docker tag registry.redhat.io/openshift4/ose-prometheus-alertmanager:4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

docker tag registry.redhat.io/openshift4/ose-prometheus:4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

Red Hat Enterprise Linux 8

podman tag registry.redhat.io/rhceph/rhceph-4-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman tag registry.redhat.io/openshift4/ose-prometheus-node-exporter:v4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman tag registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman tag registry.redhat.io/openshift4/ose-prometheus-alertmanager:4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman tag registry.redhat.io/openshift4/ose-prometheus:4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

Replace

- LOCAL_NODE_FQDN with your local host FQDN.
- e. Push the image to the local Docker registry you started:

Red Hat Enterprise Linux 7

```
# docker push registry.redhat.io/rhceph/rhceph-4-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

# docker push registry.redhat.io/openshift4/ose-prometheus-node-exporter:v4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

# docker push registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

# docker push registry.redhat.io/openshift4/ose-prometheus-alertmanager:4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

# docker push registry.redhat.io/openshift4/ose-prometheus:4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg
```

Red Hat Enterprise Linux 8

podman push registry.redhat.io/rhceph/rhceph-4-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman push registry.redhat.io/openshift4/ose-prometheus-node-exporter:v4.1

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman push registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8

LOCAL_NODE_FQDN:5000/cephimageinlocalreg

podman push registry.redhat.io/openshift4/ose-prometheus-alertmanager:4.1 LOCAL_NODE_FQDN:5000/cephimageinlocalreg # podman push registry.redhat.io/openshift4/ose-prometheus:4.1 LOCAL_NODE_FQDN:5000/cephimageinlocalreg

Replace

- LOCAL_NODE_FQDN with your local host FQDN.
- 2. For all deployments, bare-metal or in containers:
 - a. Register the node, and when prompted, enter the appropriate Red Hat Customer Portal credentials:
 - # subscription-manager register
 - b. Pull the latest subscription data from the CDN:
 - # subscription-manager refresh
 - c. List all available subscriptions for Red Hat Ceph Storage:
 - # subscription-manager list --available --all --matches="*Ceph*"

Identify the appropriate subscription and retrieve its Pool ID.

d. Attach the subscription:

subscription-manager attach --pool=POOL_ID

Replace

- POOL_ID with the Pool ID identified in the previous step.
- e. Disable the default software repositories, and enable the server and the extras repositories on the respective version of Red Hat Enterprise Linux:

Red Hat Enterprise Linux 7

```
# subscription-manager repos --disable=*
# subscription-manager repos --enable=rhel-7-server-rpms
# subscription-manager repos --enable=rhel-7-server-extras-rpms
```

Red Hat Enterprise Linux 8

```
# subscription-manager repos --disable=*
# subscription-manager repos --enable=rhel-8-for-x86_64-baseos-rpms
# subscription-manager repos --enable=rhel-8-for-x86_64-appstream-rpms
```

- 3. Update the system to receive the latest packages.
 - a. For Red Hat Enterprise Linux 7:

yum update

b. For Red Hat Enterprise Linux 8:

dnf update

Additional Resources

- See the *Using and Configuring Red Hat Subscription Manager* guide for Red Hat Subscription Management.
- See the Enabling the Red Hat Ceph Storage repositories.

Return to requirements checklist

2.5. ENABLING THE RED HAT CEPH STORAGE REPOSITORIES

Before you can install Red Hat Ceph Storage, you must choose an installation method. Red Hat Ceph Storage supports two installation methods:

- Content Delivery Network (CDN)
 For Ceph Storage clusters with Ceph nodes that can connect directly to the internet, use Red Hat Subscription Manager to enable the required Ceph repository.
- Local Repository
 For Ceph Storage clusters where security measures preclude nodes from accessing the internet, install Red Hat Ceph Storage 4 from a single software build delivered as an ISO image,

Prerequisites

- Valid customer subscription.
- For CDN installations:
 - Red Hat Ceph Storage nodes must be able to connect to the internet.
 - Register the cluster nodes with CDN.

which will allow you to install local repositories.

• If enabled, then disable the Extra Packages for Enterprise Linux (EPEL) software repository:

[root@monitor ~]# yum install yum-utils vim -y [root@monitor ~]# yum-config-manager --disable epel

Procedure

• For CDN installations:

On the **Ansible administration node**, enable the Red Hat Ceph Storage 4 Tools repository and Ansible repository:

Red Hat Enterprise Linux 7

[root@admin ~]# subscription-manager repos --enable=rhel-7-server-rhceph-4-tools-rpms --enable=rhel-7-server-ansible-2.8-rpms

Red Hat Enterprise Linux 8

[root@admin ~]# subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms --enable=ansible-2.8-for-rhel-8-x86_64-rpms

 By default, Red Hat Ceph Storage repositories are enabled by ceph-ansible on the respective nodes. To manually enable the repositories:



NOTE

Do not enable these repositories on containerized deployments as they are not needed.

On the **Ceph Monitor nodes**, enable the Red Hat Ceph Storage 4 Monitor repository:

Red Hat Enterprise Linux 7

[root@monitor ~]# subscription-manager repos --enable=rhel-7-server-rhceph-4-mon-rpms

Red Hat Enterprise Linux 8

[root@monitor ~]# subscription-manager repos --enable=rhceph-4-mon-for-rhel-8-x86_64-rpms

On the Ceph OSD nodes, enable the Red Hat Ceph Storage 4 OSD repository:

Red Hat Enterprise Linux 7

[root@osd ~]# subscription-manager repos --enable=rhel-7-server-rhceph-4-osd-rpms

Red Hat Enterprise Linux 8

[root@osd ~]# subscription-manager repos --enable=rhceph-4-osd-for-rhel-8-x86_64-rpms

Enable the Red Hat Ceph Storage 4 Tools repository on the following node types: **RBD** mirroring, Ceph clients, Ceph Object Gateways, Metadata Servers, NFS, iSCSI gateways, and Dashboard servers.

Red Hat Enterprise Linux 7

[root@client ~]# subscription-manager repos --enable=rhel-7-server-rhceph-4-tools-rpms

Red Hat Enterprise Linux 8

[root@client ~]# subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms

- For ISO installations:
 - 1. Log in to the Red Hat Customer Portal.

- 2. Click **Downloads** to visit the **Software & Download**center.
- 3. In the Red Hat Ceph Storage area, click **Download Software** to download the latest version of the software.

Additional Resources

• The Using and Configuring Red Hat Subscription Manager guide for Red Hat Subscription Management 1

Return to requirements checklist

2.6. CONSIDERATIONS FOR USING A RAID CONTROLLER WITH OSD NODES

Optionally, you can consider using a RAID controller on the OSD nodes. Here are some things to consider:

- If an OSD node has a RAID controller with 1-2GB of cache installed, enabling the write-back cache might result in increased small I/O write throughput. However, the cache must be non-volatile.
- Most modern RAID controllers have super capacitors that provide enough power to drain volatile memory to non-volatile NAND memory during a power-loss event. It is important to understand how a particular controller and its firmware behave after power is restored.
- Some RAID controllers require manual intervention. Hard drives typically advertise to the
 operating system whether their disk caches should be enabled or disabled by default. However,
 certain RAID controllers and some firmware do not provide such information. Verify that disk
 level caches are disabled to avoid file system corruption.
- Create a single RAID 0 volume with write-back for each Ceph OSD data drive with write-back cache enabled.
- If Serial Attached SCSI (SAS) or SATA connected Solid-state Drive (SSD) disks are also present on the RAID controller, then investigate whether the controller and firmware support pass-through mode. Enabling pass-through mode helps avoid caching logic, and generally results in much lower latency for fast media.

Return to requirements checklist

2.7. CONSIDERATIONS FOR USING NVME WITH OBJECT GATEWAY

Optionally, you can consider using NVMe for the Ceph Object Gateway.

If you plan to use the object gateway feature of Red Hat Ceph Storage and the OSD nodes are using NVMe-based SSDs, then consider following the procedures found in the *Using NVMe with LVM optimally* section of the *Ceph Object Gateway for Production Guide*. These procedures explain how to use specially designed Ansible playbooks which will place journals and bucket indexes together on SSDs, which can increase performance compared to having all journals on one device.

Return to requirements checklist

2.8. VERIFYING THE NETWORK CONFIGURATION FOR RED HAT CEPH STORAGE

All Red Hat Ceph Storage nodes require a public network. You must have a network interface card configured to a public network where Ceph clients can reach Ceph monitors and Ceph OSD nodes.

You might have a network interface card for a cluster network so that Ceph can conduct heart-beating, peering, replication, and recovery on a network separate from the public network.

Configure the network interface settings and ensure to make the changes persistent.



IMPORTANT

Red Hat does not recommend using a single network interface card for both a public and private network.

Prerequisites

Network interface card connected to the network.

Procedure

Do the following steps on all Red Hat Ceph Storage nodes in the storage cluster, as the **root** user.

- Verify the following settings are in the /etc/sysconfig/network-scripts/ifcfg-* file corresponding the public-facing network interface card:
 - a. The **BOOTPROTO** parameter is set to **none** for static IP addresses.
 - b. The **ONBOOT** parameter must be set to **yes**.
 If it is set to **no**, the Ceph storage cluster might fail to peer on reboot.
 - c. If you intend to use IPv6 addressing, you must set the IPv6 parameters such as IPV6INIT to yes, except the IPv6_FAILURE_FATAL parameter.
 Also, edit the Ceph configuration file, /etc/ceph/ceph.conf, to instruct Ceph to use IPv6, otherwise, Ceph uses IPv4.

Additional Resources

- For details on configuring network interface scripts for Red Hat Enterprise Linux 8, see the Configuring ip networking with ifcfg files chapter in the Configuring and managing networking guide for Red Hat Enterprise Linux 8.
- For more information on network configuration see the *Network Configuration Reference* chapter in the *Configuration Guide* for Red Hat Ceph Storage 4.

Return to requirements checklist

2.9. CONFIGURING A FIREWALL FOR RED HAT CEPH STORAGE

Red Hat Ceph Storage uses the **firewalld** service.

The Monitor daemons use port 6789 for communication within the Ceph storage cluster.

On each Ceph OSD node, the OSD daemons use several ports in the range 6800-7300:

- One for communicating with clients and monitors over the public network
- One for sending data to other OSDs over a cluster network, if available; otherwise, over the public network
- One for exchanging heartbeat packets over a cluster network, if available; otherwise, over the public network

The Ceph Manager (**ceph-mgr**) daemons use ports in range **6800-7300**. Consider colocating the **ceph-mgr** daemons with Ceph Monitors on same nodes.

The Ceph Metadata Server nodes (ceph-mds) use port range 6800-7300.

The Ceph Object Gateway nodes are configured by Ansible to use port **8080** by default. However, you can change the default port, for example to port **80**.

To use the SSL/TLS service, open port 443.

The following steps are optional if **firewalld** is enabled. By default, **ceph-ansible** includes the below setting in **group_vars/all.yml**, which automatically opens the appropriate ports:

configure_firewall: True

Prerequisite

- Network hardware is connected.
- Having **root** or **sudo** access to all nodes in the storage cluster.

Procedure

1. On all nodes in the storage cluster, start the **firewalld** service. Enable it to run on boot, and ensure that it is running:

```
# systemctl enable firewalld
# systemctl start firewalld
# systemctl status firewalld
```

2. On all monitor nodes, open port 6789 on the public network:

```
[root@monitor ~]# firewall-cmd --zone=public --add-port=6789/tcp [root@monitor ~]# firewall-cmd --zone=public --add-port=6789/tcp --permanent
```

To limit access based on the source address:

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \
source address="IP_ADDRESS/NETMASK_PREFIX" port protocol="tcp" \
port="6789" accept"
```

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \
source address="IP_ADDRESS/NETMASK_PREFIX" port protocol="tcp" \
port="6789" accept" --permanent
```

Replace

- IP_ADDRESS with the network address of the Monitor node.
- NETMASK PREFIX with the netmask in CIDR notation.

Example

```
[root@monitor \sim]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="192.168.0.11/24" port protocol="tcp" \ port="6789" accept"
```

```
[root@monitor ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="192.168.0.11/24" port protocol="tcp" \ port="6789" accept" --permanent
```

3. On all OSD nodes, open ports **6800-7300** on the public network:

```
[root@osd ~]# firewall-cmd --zone=public --add-port=6800-7300/tcp [root@osd ~]# firewall-cmd --zone=public --add-port=6800-7300/tcp --permanent
```

If you have a separate cluster network, repeat the commands with the appropriate zone.

4. On all Ceph Manager (**ceph-mgr**) nodes, open ports **6800-7300** on the public network:

```
[root@monitor ~]# firewall-cmd --zone=public --add-port=6800-7300/tcp [root@monitor ~]# firewall-cmd --zone=public --add-port=6800-7300/tcp --permanent
```

If you have a separate cluster network, repeat the commands with the appropriate zone.

5. On all Ceph Metadata Server (ceph-mds) nodes, open ports 6800-7300 on the public network:

```
[root@monitor ~]# firewall-cmd --zone=public --add-port=6800-7300/tcp [root@monitor ~]# firewall-cmd --zone=public --add-port=6800-7300/tcp --permanent
```

If you have a separate cluster network, repeat the commands with the appropriate zone.

- 6. On all Ceph Object Gateway nodes, open the relevant port or ports on the public network.
 - a. To open the default Ansible configured port of 8080:

```
[root@gateway ~]# firewall-cmd --zone=public --add-port=8080/tcp [root@gateway ~]# firewall-cmd --zone=public --add-port=8080/tcp --permanent
```

To limit access based on the source address:

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="IP\_ADDRESS/NETMASK\_PREFIX" port protocol="tcp" \ port="8080" accept"
```

```
\label{lem:cond} firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ \ source address="\it IP\_ADDRESS/NETMASK\_PREFIX" \ port="8080" \ accept" --permanent
```

Replace

- IP_ADDRESS with the network address of the Monitor node.
- NETMASK PREFIX with the netmask in CIDR notation.

Example

```
[root@gateway ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4"  
source address="192.168.0.31/24" port protocol="tcp" \
port="8080" accept"

[root@gateway ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4"  
source address="192.168.0.31/24" port protocol="tcp" \
port="8080" accept" --permanent
```

b. Optionally, if you installed Ceph Object Gateway using Ansible and changed the default port that Ansible configures the Ceph Object Gateway to use from 8080, for example, to port 80, then open this port:

```
[root@gateway ~]# firewall-cmd --zone=public --add-port=80/tcp [root@gateway ~]# firewall-cmd --zone=public --add-port=80/tcp --permanent
```

To limit access based on the source address, run the following commands:

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \
source address="IP_ADDRESS/NETMASK_PREFIX" port protocol="tcp" \
port="80" accept"
```

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="IP_ADDRESS/NETMASK_PREFIX" port protocol="tcp" \ port="80" accept" --permanent
```

Replace

- IP_ADDRESS with the network address of the Monitor node.
- NETMASK_PREFIX with the netmask in CIDR notation.

Example

```
[root@gateway ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="192.168.0.31/24" port protocol="tcp" \ port="80" accept"
```

```
[root@gateway ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="192.168.0.31/24" port protocol="tcp" \ port="80" accept" --permanent
```

c. Optional. To use SSL/TLS, open port 443:

```
[root@gateway ~]# firewall-cmd --zone=public --add-port=443/tcp [root@gateway ~]# firewall-cmd --zone=public --add-port=443/tcp --permanent
```

To limit access based on the source address, run the following commands:

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="IP_ADDRESS/NETMASK_PREFIX" port protocol="tcp" \ port="443" accept"
```

```
firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \
source address="IP_ADDRESS/NETMASK_PREFIX" port protocol="tcp" \
port="443" accept" --permanent
```

Replace

- IP_ADDRESS with the network address of the Monitor node.
- NETMASK PREFIX with the netmask in CIDR notation.

Example

```
[root@gateway ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="192.168.0.31/24" port protocol="tcp" \ port="443" accept" [root@gateway ~]# firewall-cmd --zone=public --add-rich-rule="rule family="ipv4" \ source address="192.168.0.31/24" port protocol="tcp" \ port="443" accept" --permanent
```

Additional Resources

- For more information about public and cluster network, see Verifying the Network Configuration for Red Hat Ceph Storage.
- For additional details on **firewalld**, see the Using and configuring firewalls chapter in the Securing networks guide for Red Hat Enterprise Linux 8.

Return to requirements checklist

2.10. CREATING AN ANSIBLE USER WITH SUDO ACCESS

Ansible must be able to log into all the Red Hat Ceph Storage (RHCS) nodes as a user that has **root** privileges to install software and create configuration files without prompting for a password. You must create an Ansible user with password-less **root** access on all nodes in the storage cluster when deploying and configuring a Red Hat Ceph Storage cluster with Ansible.

Prerequisite

• Having **root** or **sudo** access to all nodes in the storage cluster.

Procedure

1. Log into the node as the **root** user:

ssh root@HOST_NAME

Replace

• HOST_NAME with the host name of the Ceph node.

Example

ssh root@mon01

Enter the **root** password when prompted.

2. Create a new Ansible user:

adduser USER_NAME

Replace

• USER_NAME with the new user name for the Ansible user.

Example

adduser admin



IMPORTANT

Do not use **ceph** as the user name. The **ceph** user name is reserved for the Ceph daemons. A uniform user name across the cluster can improve ease of use, but avoid using obvious user names, because intruders typically use them for brute-force attacks.

3. Set a new password for this user:

passwd USER_NAME

Replace

• USER_NAME with the new user name for the Ansible user.

Example

passwd admin

Enter the new password twice when prompted.

4. Configure **sudo** access for the newly created user:

cat << EOF >/etc/sudoers.d/*USER_NAME* \$USER_NAME ALL = (root) NOPASSWD:ALL EOF

Replace

• USER_NAME with the new user name for the Ansible user.

Example

cat << EOF >/etc/sudoers.d/admin admin ALL = (root) NOPASSWD:ALL EOF

5. Assign the correct file permissions to the new file:

chmod 0440 /etc/sudoers.d/USER_NAME

Replace

• USER_NAME with the new user name for the Ansible user.

Example

chmod 0440 /etc/sudoers.d/admin

Additional Resources

• The Managing user accounts section in the *Configuring basic system settings* guide Red Hat Enterprise Linux 8

Return to requirements checklist

2.11. ENABLING PASSWORD-LESS SSH FOR ANSIBLE

Generate an SSH key pair on the Ansible administration node and distribute the public key to each node in the storage cluster so that Ansible can access the nodes without being prompted for a password.



NOTE

This procedure is not required if installing Red Hat Ceph Storage using the Cockpit webbased interface. This is because the Cockpit Ceph Installer generates its own SSH key. Instructions for copying the Cockpit SSH key to all nodes in the cluster—are in the chapter Installing Red Hat Ceph Storage using the Cockpit web interface.

Prerequisites

- Access to the Ansible administration node.
- Creating an Ansible user with **sudo** access.

Procedure

1. Generate the SSH key pair, accept the default file name and leave the passphrase empty:

[ansible@admin ~]\$ ssh-keygen

2. Copy the public key to all nodes in the storage cluster:

ssh-copy-id USER_NAME@HOST_NAME

Replace

- USER_NAME with the new user name for the Ansible user.
- HOST_NAME with the host name of the Ceph node.

Example

[ansible@admin ~]\$ ssh-copy-id ceph-admin@ceph-mon01

3. Create the user's SSH config file:

[ansible@admin ~]\$ touch ~/.ssh/config

4. Open for editing the **config** file. Set values for the **Hostname** and **User** options for each node in the storage cluster:

Host node1
Hostname HOST_NAME
User USER_NAME
Host node2
Hostname HOST_NAME
User USER_NAME

Replace

- HOST_NAME with the host name of the Ceph node.
- USER_NAME with the new user name for the Ansible user.

Example

Host node1
Hostname monitor
User admin
Host node2
Hostname osd
User admin
Host node3
Hostname gateway
User admin



IMPORTANT

By configuring the ~/.ssh/config file you do not have to specify the -u *USER_NAME* option each time you execute the ansible-playbook command.

5. Set the correct file permissions for the ~/.ssh/config file:

[admin@admin ~]\$ chmod 600 ~/.ssh/config

Additional Resources

- The **ssh_config(5)** manual page.
- See the Using secure communications between two systems with OpenSSH chapter in the Securing networks for Red Hat Enterprise Linux 8.

Return to requirements checklist

2.12. CONFIGURING ANSIBLE INVENTORY LOCATION

As an option, you can configure inventory location files for the **ceph-ansible** staging and production environments.

Prerequisites

- An Ansible administration node.
- Root-level access to the Ansible administration node.
- The **ceph-ansible** package installed on the node.

Procedure

- 1. Navigate to the /usr/share/ceph-ansible directory:
 - [root@admin ~]# cd /usr/share/ceph-ansible
- 2. Create subdirectories for staging and production:
 - [root@admin ~]# mkdir -p inventory/staging inventory/production
- 3. Edit the **ansible.cfg** file and add the following lines:

[defaults]
+ inventory = ./inventory/staging # Assign a default inventory directory

4. Create an inventory 'hosts' file for each environment:

[root@admin ~]# touch inventory/staging/hosts [root@admin ~]# touch inventory/production/hosts

a. Open and edit each **hosts** file and add the Ceph Monitor nodes under the **[mons]** section:

[mons]

MONITOR_NODE_NAME_1

MONITOR_NODE_NAME_1

MONITOR_NODE_NAME_1

Example

[mons] mon-stage-node1 mon-stage-node2 mon-stage-node3



NOTE

By default, playbooks run in the staging environment. To run the playbook in the production environment:

[root@admin ~]# ansible-playbook -i inventory/production playbook.yml

Additional Resources

• For more information about installing the **ceph-ansible** package, see Installing a Red Hat Storage Cluster.

CHAPTER 3. INSTALLING RED HAT CEPH STORAGE USING THE COCKPIT WEB INTERFACE

This chapter describes how to use the Cockpit web-based interface to install a Red Hat Ceph Storage cluster and other components, such as Metadata Servers, the Ceph client, or the Ceph Object Gateway.

The process consists of installing the Cockpit Ceph Installer, logging into Cockpit, and configuring and starting the cluster install using different pages within the installer.



NOTE

The Cockpit Ceph Installer uses Ansible and the Ansible playbooks provided by the **ceph-ansible** RPM to perform the actual install. It is still possible to use these playbooks to install Ceph without Cockpit. That process is relevant to this chapter and is referred to as a *direct Ansible install*, or *using the Ansible playbooks directly*.



IMPORTANT

The Cockpit Ceph installer does not currently support IPv6 networking. If you require IPv6 networking, install Ceph using the Ansible playbooks directly.



NOTE

The dashboard web interface, used for administration and monitoring of Ceph, is installed by default by the Ansible playbooks in the **ceph-ansible** RPM, which Cockpit uses on the back-end. Therefore, whether you use Ansible playbooks directly, or use Cockpit to install Ceph, the dashboard web interface will be installed as well.

3.1. PREREQUISITES

- Complete the general prerequisites required for direct Ansible Red Hat Ceph Storage installs.
- A recent version of Firefox or Chrome.
- If using multiple networks to segment intra-cluster traffic, client-to-cluster traffic, RADOS Gateway traffic, or iSCSI traffic, ensure the relevant networks are already configured on the hosts. For more information, see network considerations in the Hardware Guide and the section in this chapter on completing the Network page of the Cockpit Ceph Installer
- Ensure the default port for Cockpit web-based interface, **9090**, is accessible.

3.2. INSTALLATION REQUIREMENTS

- One node to act as the Ansible administration node.
- One node to provide the performance metrics and alerting platform. This may be colocated with the Ansible administration node.
- One or more nodes to form the Ceph cluster. The installer supports an all-in-one installation called *Development/POC*. In this mode all Ceph services can run from the same node, and data replication defaults to disk rather than host level protection.

3.3. INSTALL AND CONFIGURE THE COCKPIT CEPH INSTALLER

Before you can use the Cockpit Ceph Installer to install a Red Hat Ceph Storage cluster, you must install the Cockpit Ceph Installer on the Ansible administration node.

Prerequisites

- Root-level access to the Ansible administration node.
- The **ansible** user account for use with the Ansible application.

Procedure

1. Verify Cockpit is installed.

\$ rpm -q cockpit

Example:

[admin@jb-ceph4-admin ~]\$ rpm -q cockpit cockpit-196.3-1.el8.x86_64

If you see similar output to the example above, skip to the step *Verify Cockpit is running*. If the output is **package cockpit is not installed**, continue to the step *Install Cockpit*.

- 2. Optional: Install Cockpit.
 - a. For Red Hat Enterprise Linux 8:
 - # dnf install cockpit
 - b. For Red Hat Enterprise Linux 7:
 - # yum install cockpit
- 3. Verify Cockpit is running.
 - # systemctl status cockpit.socket

If you see **Active: active (listening)** in the output, skip to the step *Install the Cockpit plugin for Red Hat Ceph Storage*. If instead you see **Active: inactive (dead)**, continue to the step *Enable Cockpit*.

- 4. Optional: Enable Cockpit.
 - a. Use the **systemctl** command to enable Cockpit:
 - # systemctl enable --now cockpit.socket

You will see a line like the following:

Created symlink /etc/systemd/system/sockets.target.wants/cockpit.socket → /usr/lib/systemd/system/cockpit.socket.

b. Verify Cockpit is running:

systemctl status cockpit.socket

You will see a line like the following:

Active: active (listening) since Tue 2020-01-07 18:49:07 EST; 7min ago

- 5. Install the Cockpit Ceph Installer for Red Hat Ceph Storage.
 - a. For Red Hat Enterprise Linux 8:

dnf install cockpit-ceph-installer

b. For Red Hat Enterprise Linux 7:

yum install cockpit-ceph-installer

6. As the Ansible user, log in to the container catalog using sudo:



NOTE

By default, the Cockpit Ceph Installer uses the **root** user to install Ceph. To use the Ansible user created as a part of the prerequisites to install Ceph, run the rest of the commands in this procedure with **sudo** as the Ansible user.

Red Hat Enterprise Linux 7

\$ sudo docker login -u CUSTOMER_PORTAL_USERNAME https://registry.redhat.io

Example

[admin@jb-ceph4-admin ~]\$ sudo docker login -u myusername https://registry.redhat.io Password:

Login Succeeded!

Red Hat Enterprise Linux 8

\$ sudo podman login -u CUSTOMER_PORTAL_USERNAME https://registry.redhat.io

Example

[admin@jb-ceph4-admin ~]\$ sudo podman login -u myusername https://registry.redhat.io Password:

Login Succeeded!

- 7. Verify **registry.redhat.io** is in the container registry search path.
 - a. Open for editing the /etc/containers/registries.conf file:

[registries.search]
registries = ['registry.access.redhat.com', 'registry.fedoraproject.org',
'registry.centos.org', 'docker.io']

If registry.redhat.io is not included in the file, add it:

[registries.search]
registries = ['registry.redhat.io', 'registry.access.redhat.com', 'registry.fedoraproject.org', 'registry.centos.org', 'docker.io']

8. As the Ansible user, start the **ansible-runner-service** using sudo.

\$ sudo ansible-runner-service.sh -s

Example

```
[admin@jb-ceph4-admin ~]$ sudo ansible-runner-service.sh -s
Checking environment is ready
Checking/creating directories
Checking SSL certificate configuration
Generating RSA private key, 4096 bit long modulus (2 primes)
   .....
.....++++
e is 65537 (0x010001)
Generating RSA private key, 4096 bit long modulus (2 primes)
   .....++++
.....
.....++++
e is 65537 (0x010001)
writing RSA key
Signature ok
subject=C = US, ST = North Carolina, L = Raleigh, O = Red Hat, OU = RunnerServer, CN =
jb-ceph4-admin
Getting CA Private Key
Generating RSA private key, 4096 bit long modulus (2 primes)
.....++++
e is 65537 (0x010001)
writing RSA key
Signature ok
subject=C = US, ST = North Carolina, L = Raleigh, O = Red Hat, OU = RunnerClient, CN = jb-
ceph4-admin
Getting CA Private Key
Setting ownership of the certs to your user account(admin)
Setting target user for ansible connections to admin
Applying SELINUX container file t context to '/etc/ansible-runner-service'
Applying SELINUX container file t context to '/usr/share/ceph-ansible'
Ansible API (runner-service) container set to rhceph/ansible-runner-rhel8:latest
Fetching Ansible API container (runner-service). Please wait...
Trying to pull registry.redhat.io/rhceph/ansible-runner-rhel8:latest...Getting image source
signatures
Copying blob c585fd5093c6 done
Copying blob 217d30c36265 done
Copying blob e61d8721e62e done
Copying config b96067ea93 done
Writing manifest to image destination
Storing signatures
b96067ea93c8d6769eaea86854617c63c61ea10c4ff01ecf71d488d5727cb577
```

Starting Ansible API container (runner-service)
Started runner-service container
Waiting for Ansible API container (runner-service) to respond
The Ansible API container (runner-service) is available and responding to requests

Login to the cockpit UI at https://jb-ceph4-admin:9090/cockpit-ceph-installer to start the install

The last line of output includes the URL to the Cockpit Ceph Installer. In the example above the URL is https://jb-ceph4-admin:9090/cockpit-ceph-installer. Take note of the URL printed in your environment.

3.4. COPY THE COCKPIT CEPH INSTALLER SSH KEY TO ALL NODES IN THE CLUSTER

The Cockpit Ceph Installer uses SSH to connect to and configure the nodes in the cluster. In order for it to do this automatically the installer generates an SSH key pair so it can access the nodes without being prompted for a password. The SSH public key must be transferred to all nodes in the cluster.

Prerequisites

- An Ansible user with sudo access has been created.
- The Cockpit Ceph Installer is installed and configured.

Procedure

1. Log in to the Ansible administration node as the Ansible user.

ssh ANSIBLE_USER@HOST_NAME

Example:

\$ ssh admin@jb-ceph4-admin

2. Copy the SSH public key to the first node:

sudo ssh-copy-id -f -i /usr/share/ansible-runner-service/env/ssh_key.pub _ANSIBLE_USER_@_HOST_NAME_

Example:

\$ sudo ssh-copy-id -f -i /usr/share/ansible-runner-service/env/ssh_key.pub admin@jb-ceph4-mon

/bin/ssh-copy-id: INFO: Source of key(s) to be installed: "/usr/share/ansible-runner-service/env/ssh_key.pub" admin@192.168.122.182's password:

Number of key(s) added: 1

Now try logging into the machine, with: "ssh 'admin@jb-ceph4-mon'" and check to make sure that only the key(s) you wanted were added.

Repeat this step for all nodes in the cluster

3.5. LOG IN TO COCKPIT


You can view the Cockpit Ceph Installer web interface by logging into Cockpit.

Prerequisites


- The Cockpit Ceph Installer is installed and configured.
- You have the URL printed as a part of configuring the Cockpit Ceph Installer

Procedure


1. Open the URL in a web browser.




2. Enter the Ansible user name and its password.




3. Click the radio button for Reuse my password for privileged tasks.



4. Click Log In.



5. Review the welcome page to understand how the installer works and the overall flow of the installation process.



Click the *Environment* button at the bottom right corner of the web page after you have reviewed the information in the welcome page.

3.6. COMPLETE THE ENVIRONMENT PAGE OF THE COCKPIT CEPH INSTALLER

The *Environment* page allows you to configure overall aspects of the cluster, like what installation source to use and how to use Hard Disk Drives (HDDs) and Solid State Drives (SSDs) for storage.

Prerequisites

- The Cockpit Ceph Installer is installed and configured.
- You have the URL printed as a part of configuring the Cockpit Ceph Installer.
- You have created a registry service account.




NOTE

In the dialogs to follow, there are tooltips to the right of some of the settings. To view them, hover the mouse cursor over the icon that looks like an *i* with a circle around it.

Procedure

1. Select the *Installation Source*. Choose *Red Hat* to use repositories from Red Hat Subscription Manager, or ISO to use a CD image downloaded from the Red Hat Customer Portal.



If you choose *Red Hat*, *Target Version* will be set to *RHCS 4* without any other options. If you choose *ISO*, *Target Version* will be set to the ISO image file.



IMPORTANT

If you choose ISO, the image file must be in the /usr/share/ansible-runner-service/iso directory and its SELinux context must be set to container_file_t.




IMPORTANT

The Community and Distribution options for Installation Source are not supported.

2. Select the *Cluster Type*. The *Production* selection prohibits the install from proceeding if certain resource requirements like CPU number and memory size are not met. To allow the cluster installation to proceed even if the resource requirements are not met, select *Development/POC*.

1. Environment

Define the high level environment settings that will determine the way that the Ceph cluster is installed and configured.






IMPORTANT

Do not use *Development/POC* mode to install a Ceph cluster that will be used in production.

3. Set the Service Account Login and Service Account Token. If you do not have a Red Hat Registry Service Account, create one using the Registry Service Account webpage.



4. Set Configure Firewall to ON to apply rules to **firewalld** to open ports for Ceph services. Use the OFF setting if you are not using **firewalld**.



5. Currently, the Cockpit Ceph Installer only supports IPv4. If you require IPv6 support, discountinue use of the Cockpit Ceph Installer and proceed with installing Ceph using the Ansible scripts directly.





IMPORTANT

BlueStore is the default OSD type. Previously, Ceph used FileStore as the object store. This format is deprecated for new Red Hat Ceph Storage 4.0 installs because BlueStore offers more features and improved performance. It is still possible to use FileStore, but using it requires a support exception. For more information on BlueStore, see Ceph BlueStore in the Architecture Guide.

7. Set Flash Configuration to Journal/Logs or OSD data. If you have Solid State Drives (SSDs), whether they use NVMe or a traditional SATA/SAS interface, you can choose to use them just for write journaling and logs while the actual data goes on Hard Disk Drives (HDDs), or you can use the SSDs for journaling, logs, and data, and not use HDDs for any Ceph OSD functions.

Flash Configuration ① Flash media (SSD or NVMe) can be used for all data, or as journal devices to improve the performance of slower devices (HDDs)

② Journals/Logs ② OSD Data

8. Set *Encryption* to *None* or *Encrypted*. This refers to at rest encryption of storage devices using the LUKS1 format.

Encryption ① For added security, you may use at-rest encryption for your storage devices

None Encrypted


9. Set *Installation type* to *Container* or *RPM*. Traditionally, Red Hat Package Manager (RPM) was used to install software on Red Hat Enterprise Linux. Now, you can install Ceph using RPM or containers. Installing Ceph using containers can provide improved hardware utilization since services can be isolated and collocated.

Ceph can be installed as lightweight container images, or as rpm packages. Container deployments offer service isolation enabling improved collocation and hardware utilization

Container

RPM

10. Review all the Environment settings and click the *Hosts* button at the bottom right corner of the webpage.



3.7. COMPLETE THE HOSTS PAGE OF THE COCKPIT CEPH INSTALLER


The *Hosts* page allows you inform the Cockpit Ceph Installer what hosts to install Ceph on, and what roles each host will be used for. As you add the hosts, the installer will check them for SSH and DNS connectivity.

Prerequisites


- The Environment page of the Cockpit Ceph Installer has been completed.
- The Cockpit Ceph Installer SSH key has been copied to all nodes in the cluster .

Procedure

1. Click the Add Host(s) button.



2. Enter the hostname for a Ceph OSD node, check the box for OSD, and click the Add button.




The first Ceph OSD node is added.




For production clusters, repeat this step until you have added at least three Ceph OSD nodes.

3. Optional: Use a host name pattern to define a range of nodes. For example, to add **jb-ceph4-osd2** and **jb-ceph4-osd3** at the same time, enter **jb-ceph4-osd[2-3]**.




Both jb-ceph4-osd2 and jb-ceph4-ods3 are added.




- 4. Repeat the above steps for the other nodes in your cluster.
 - a. For production clusters, add at least three Ceph Monitor nodes. In the dialog, the role is listed as **MON**.
 - b. Add a node with the **Metrics** role. The **Metrics** role installs Grafana and Prometheus to provide real-time insights into the performance of the Ceph cluster. These metrics are presented in the Ceph Dashboard, which allows you to monitor and manage the cluster. The installation of the dashboard, Grafana, and Prometheus are required. You can colocate the metrics functions on the Ansible Administration node. If you do, ensure the system resources of the node are greater than what is required for a stand alone metrics node.
 - c. Optional: Add a node with the **MDS** role. The **MDS** role installs the Ceph Metadata Server (MDS). Metadata Server daemons are necessary for deploying a Ceph File System.
 - d. Optional: Add a node with the **RGW** role. The **RGW** role installs the Ceph Object Gateway, also know as the RADOS gateway, which is an object storage interface built on top of the librados API to provide applications with a RESTful gateway to Ceph storage clusters. It supports the Amazon S3 and OpenStack Swift APIs.

- e. Optional: Add a node with the **iSCSI** role. The **iSCSI** role installs an iSCSI gateway so you can share Ceph Block Devices over iSCSI. To use iSCSI with Ceph, you must install the iSCSI gateway on at least two nodes for multipath I/O.
- 5. Optional: Colocate more than one service on the same node by selecting multiple roles when adding the node.




For more information on colocating daemons, see Colocation of containerized Ceph daemons in the Installation Guide.


6. Optional: Modify the roles assigned to a node by checking or unchecking roles in the table.



7. Optional: To delete a node, on the far right side of the row of the node you want to delete, click the kebab icon and then click *Delete*.



8. Click the *Validate* button at the bottom right corner of the page after you have added all the nodes in your cluster and set all the required roles.





NOTE

For production clusters, the Cockpit Ceph installer will not proceed unless you have three or five monitors. In these examples *Cluster Type* is set to *Development/POC* so the install can proceed with only one monitor.

3.8. COMPLETE THE VALIDATE PAGE OF THE COCKPIT CEPH INSTALLER


The *Validate* page allows you to probe the nodes you provided on the *Host*s page to verify they meet the hardware requirements for the roles you intend to use them for.

Prerequisites

• The Hosts page of the Cockpit Ceph Installer has been completed.


Procedure

1. Click the *Probe Hosts* button.



To continue you must select at least three hosts which have an OK Status.

2. Optional: If warnings or errors were generated for hosts, click the arrow to the left of the check mark for the host to view the issues.





IMPORTANT


If you set *Cluster Type* to *Production*, any errors generated will cause *Status* to be *NOTOK* and you will not be able to select them for installation. Read the next step for information on how to resolve errors.



IMPORTANT


If you set *Cluster Type* to *Development/POC*, any errors generated will be listed as warnings so *Status* is always *OK*. This allows you to select the hosts and install Ceph on them regardless of whether the hosts meet the requirements or suggestions. You can still resolve warnings if you want to. Read the next step for information on how to resolve warnings.

- 3. Optional: To resolve errors and warnings use one or more of the following methods.
 - a. The easiest way to resolve errors or warnings is to disable certain roles completely or to disable a role on one host and enable it on another host which has the required resources. Experiment with enabling or disabling roles until you find a combination where, if you are installing a *Development/POC* cluster, you are comfortable proceeding with any remaining warnings, or if you are installing a *Production* cluster, at least three hosts have all the resources required for the roles assigned to them and you are comfortable proceeding with any remaining warnings.
 - b. You can also use a new host which meets the requirements for the roles required. First go back to the *Hosts* page and delete the hosts with issues.



Then, add the new hosts.

- c. If you want to upgrade the hardware on a host or modify it in some other way so it will meet the requirements or suggestions, first make the desired changes to the host, and then click *Probe Hosts* again. If you have to reinstall the operating system you will have to copy the SSH key again.
- 4. Select the hosts to install Red Hat Ceph Storage on by checking the box next to the host.






IMPORTANT

If installing a production cluster, you must resolve any errors before you can select them for installation.

5. Click the *Network* button at the bottom right corner of the page to review and configure networking for the cluster.



3.9. COMPLETE THE NETWORK PAGE OF THE COCKPIT CEPH INSTALLER

The *Network* page allows you to isolate certain cluster communication types to specific networks. This requires multiple different networks configured across the hosts in the cluster.



IMPORTANT

The Network page uses information gathered from the probes done on the Validate page to display the networks your hosts have access to. Currently, if you have already proceeded to the Network page, you cannot add new networks to hosts, go back to the Validate page, reprobe the hosts, and proceed to the Network page again and use the new networks. They will not be displayed for selection. To use networks added to the hosts after already going to the Network page you must refresh the web page completely and restart the install from the beginning.



IMPORTANT


For production clusters you must segregate intra-cluster-traffic from client-to-cluster traffic on separate NICs. In addition to segregating cluster traffic types, there are other networking considerations to take into account when setting up a Ceph cluster. For more information, see Network considerations in the Hardware Guide.

Prerequisites

• The Validate page of the Cockpit Ceph Installer has been completed.

Procedure


1. Take note of the network types you can configure on the Network page. Each type has its own column. Columns for *Cluster Network* and *Public Network* are always displayed. If you are installing hosts with the RADOS Gateway role, the *S3 Network* column will be displayed. If you are installing hosts with the iSCSI role, the *iSCSI Network* column will be displayed. In the example below, columns for *Cluster Network*, *Public Network*, and *S3 Network* are shown.



2. Take note of the networks you can select for each network type. Only the networks which are available on all hosts that make up a particular network type are shown. In the example below, there are three networks which are available on all hosts in the cluster. Because all three networks are available on every set of hosts which make up a network type, each network type lists the same three networks.

4. Network Configuration

The network topology plays a significant role in determining the performance of Ceph services. An optimum network configuration uses a front-end (public) and backend (cluster) network topology. This strategy separates network loads like object replication from client workload (I/O). The probe performed against your hosts has revealed the following networking options;



The three networks available are 192.168.122.0/24, 192.168.123.0/24, and 192.168.124.0/24.

3. Take note of the speed each network operates at. This is the speed of the NICs used for the particular network. In the example below, **192.168.123.0/24**, and **192.168.124.0/24** are at 1,000 mbps. The Cockpit Ceph Installer could not determine the speed for the **192.168.122.0/24** network.

4. Network Configuration

The network topology plays a significant role in determining the performance of Ceph services. An optimum network configuration uses a front-end (public) and backend (cluster) network topology. This strategy separates network loads like object replication from client workload (I/O). The probe performed against your hosts has revealed the following networking options;



4. Select the networks you want to use for each network type. For production clusters, you must select separate networks for *Cluster Network* and *Public Network*. For development/POC clusters, you can select the same network for both types, or if you only have one network configured on all hosts, only that network will be displayed and you will not be able to select other networks.


4. Network Configuration

The network topology plays a significant role in determining the performance of Ceph services. An optimum network configuration uses a front-end (public) and backend (cluster) network topology. This strategy separates network loads like object replication from client workload (I/O). The probe performed against your hosts has revealed the following networking options:



The **192.168.122.0/24** network will be used for the *Public Network*, the **192.168.123.0/24** network will be used for the *Cluster Network*, and the **192.168.124.0/24** network will be used for the *S3 Network*.

5. Click the *Review* button at the bottom right corner of the page to review the entire cluster configuration before installation.



3.10. REVIEW THE INSTALLATION CONFIGURATION


The *Review* page allows you to view all the details of the Ceph cluster installation configuration that you set on the previous pages, and details about the hosts, some of which were not included in previous pages.

Prerequisites


• The Network page of the Cockpit Ceph Installer has been completed.

Procedure


1. View the review page.



2. Verify the information from each previous page is as you expect it as shown on the *Review* page. A summary of information from the *Environment* page is at 1, followed by the *Hosts* page at 2, the *Validate* page at 3, the *Network* page at 4, and details about the hosts, including some additional details which were not included in previous pages, are at 5.



3. Click the *Deploy* button at the bottom right corner of the page to go to the *Deploy* page where you can finalize and start the actual installation process.



3.11. DEPLOY THE CEPH CLUSTER


The *Deploy* page allows you save the installation settings in their native Ansible format, review or modify them if required, start the install, monitor its progress, and view the status of the cluster after the install finishes successfully.

Prerequisites


Installation configuration settings on the Review page have been verified.

Procedure

1. Click the Save button at the bottom right corner of the page to save the installation settings to the Ansible playbooks that will be used by Ansible to perform the actual install.




- 2. Optional: View or further customize the settings in the Ansible playbooks located on the Ansible administration node. The playbooks are located in /usr/share/ceph-ansible. For more information about the Ansible playbooks and how to use them to customize the install, see Installing a Red Hat Ceph Storage cluster.
- 3. Secure the default user names and passwords for Grafana and dashboard. Starting with Red Hat Ceph Storage 4.1, you must uncomment or set dashboard_admin_password and grafana_admin_password in /usr/share/ceph-ansible/group_vars/all.yml. Set secure passwords for each. Also set custom user names for dashboard_admin_user and grafana_admin_user.
- 4. Click the Deploy button at the bottom right corner of the page to start the install.




5. Observe the installation progress while it is running.

The information at 1 shows whether the install is running or not, the start time, and elapsed time. The information at 2 shows a summary of the Ansible tasks that have been attempted. The information at 3 shows which roles have been installed or are installing. Green represents a role where all hosts that were assigned that role have had that role installed on them. Blue represents a role where hosts that have that role assigned to them are still being installed. At 4 you can view details about the current task or view failed tasks. Use the *Filter by* menu to switch between current task and failed tasks.



The role names come from the Ansible inventory file. The equivalency is: **mons** are Monitors, **mgrs** are Managers, note the Manager role is installed alongside the Monitor role, **osds** are Object Storage Devices, **mdss** are Metadata Servers, **rgws** are RADOS Gateways, **metrics** are Grafana and Prometheus services for dashboard metrics. Not shown in the example screenshot: **iscsigws** are iSCSI Gateways.


6. After the installation finishes, click the *Complete* button at the bottom right corner of the page. This opens a window which displays the output of the command **ceph status**, as well as dashboard access information.




7. Compare cluster status information in the example below with the cluster status information on your cluster. The example shows a healthy cluster, with all OSDs up and in, and all services active. PGs are in the **active+clean** state. If some aspects of your cluster are not the same, refer to the Troubleshoting Guide for information on how to resolve the issues.



8. At the bottom of the Ceph Cluster Status window, the dashboard access information is displayed, including the URL, user name, and password. Take note of this information.



9. Use the information from the previous step along with the Dashboard Guide to access the dashboard.



The dashboard provides a web interface so you can administer and monitor the Red Hat Ceph Storage cluster. For more information, see the Dashboard Guide.

10. Optional: View the **cockpit-ceph-installer.log** file. This file records a log of the selections made and any associated warnings the probe process generated. It is located in the home directory of the user that ran the installer script, **ansible-runner-service.sh**.

CHAPTER 4. INSTALLING RED HAT CEPH STORAGE USING ANSIBLE

This chapter describes how to use the Ansible application to deploy a Red Hat Ceph Storage cluster and other components, such as Metadata Servers or the Ceph Object Gateway.

- To install a Red Hat Ceph Storage cluster, see Section 4.2, "Installing a Red Hat Ceph Storage cluster".
- To install Metadata Servers, see Section 4.4, "Installing Metadata servers".
- To install the **ceph-client** role, see Section 4.5, "Installing the Ceph Client Role".
- To install the Ceph Object Gateway, see Section 4.6, "Installing the Ceph Object Gateway" .
- To configure a multisite Ceph Object Gateway, see Section 4.7, "Configuring multisite Ceph Object Gateways".
- To learn about the Ansible --limit option, see Section 4.10, "Understanding the limit option".


4.1. PREREQUISITES

- Obtain a valid customer subscription.
- Prepare the cluster nodes, by doing the following on each node:
 - Register the node to the Content Delivery Network (CDN) and attach subscriptions .
 - Enable the appropriate software repositories.
 - Create an Ansible user.
 - Enable passwordless SSH access.
 - Optionally, configure a firewall.
- Before installing with ceph-ansible, edit the inventory file and specify a node by its hostname or IP address under the [grafana-server] group where the Grafana and Prometheus instance for the Dashboard will be installed.

4.2. INSTALLING A RED HAT CEPH STORAGE CLUSTER

Use the Ansible application with the **ceph-ansible** playbook to install Red Hat Ceph Storage on baremetal or in containers. Using a Ceph storage clusters in production must have a minimum of three monitor nodes and three OSD nodes containing multiple OSD daemons. A typical Ceph storage cluster running in production usually consists of ten or more nodes.

In the following procedure, run the commands from the Ansible administration node, unless instructed otherwise. This procedure applies to both bare-metal and container deployments, unless specified.



CEPH 405148 0616



IMPORTANT

Ceph can run with one monitor; however, to ensure high availability in a production cluster, Red Hat will only support deployments with at least three monitor nodes.



IMPORTANT

Deploying Red Hat Ceph Storage 4 in containers on Red Hat Enterprise Linux 7.7 will deploy Red Hat Ceph Storage 4 on a Red Hat Enterprise Linux 8 container image.

Prerequisites

- A valid customer subscription.
- Root-level access to the Ansible administration node.
- The **ansible** user account for use with the Ansible application.
- Enable Red Hat Ceph Storage Tools and Ansible repositories
- For **ISO** installation, download the latest ISO image on the ansible node. See the section For ISO Installations in Enabling the Red Hat Ceph Storage repositories chapter in the Red Hat Ceph Storage Installation Guide.

Procedure

- 1. Log in as the **root** user account on the Ansible administration node.
- 2. For all deployments, bare-metal or in containers, install the ceph-ansible package:

Red Hat Enterprise Linux 7

[root@admin ~]# yum install ceph-ansible

Red Hat Enterprise Linux 8

- [root@admin ~]# dnf install ceph-ansible
- 3. Navigate to the /usr/share/ceph-ansible/ directory:

[root@admin ~]\$ cd /usr/share/ceph-ansible

4. Create new yml files:

[root@admin ceph-ansible]# cp group_vars/all.yml.sample group_vars/all.yml [root@admin ceph-ansible]# cp group_vars/osds.yml.sample group_vars/osds.yml

a. Bare-metal deployments:

[root@admin ceph-ansible]# cp site.yml.sample site.yml

b. Container deployments:

[root@admin ceph-ansible]# cp site-docker.yml.sample site-docker.yml

- 5. Edit the new files.
 - a. Open for editing the group_vars/all.yml file.



IMPORTANT

Using a custom storage cluster name is not supported. Do not set the **cluster** parameter to any value other than **ceph**. Using a custom storage cluster name is only supported with Ceph clients, such as: **librados**, the Ceph Object Gateway, and RADOS block device mirroring.



WARNING

By default, Ansible attempts to restart an installed, but masked **firewalld** service, which can cause the Red Hat Ceph Storage deployment to fail. To work around this issue, set the **configure_firewall** option to **false** in the **all.yml** file. If you are running the **firewalld** service, then there is no requirement to use the **configure_firewall** option in the **all.yml** file.



NOTE

Having the **ceph_rhcs_version** option set to **4** will pull in the latest version of Red Hat Ceph Storage 4.



NOTE

Red Hat recommends leaving the **dashboard_enabled** option set to **True** in the **group_vars/all.yml** file, and not changing it to **False**. If you want to disable the dashboard, see Disabling the Ceph Dashboard



NOTE

Dashboard related components are containerized. Therefore, for Bare-metal or Container deployment, 'ceph_docker_registry_username' and 'ceph_docker_registry_password' parameters have to be included so that ceph-ansible can fetch container images required for the dashboard.



NOTE

If you do not have a Red Hat Registry Service Account, create one using the Registry Service Account webpage.

i. Bare-metal example of the all.yml file for CDN installation:

fetch directory: ~/ceph-ansible-keys

ceph_origin: repository ceph_repository: rhcs ceph_repository_type: cdn ceph_rhcs_version: 4 bootstrap dirs owner: "167" bootstrap_dirs_group: "167" monitor_interface: eth0

public_network: 192.168.0.0/24

ceph docker registry: registry.redhat.io

ceph docker registry auth: true

ceph_docker_registry_username: <service-account-user-name>

ceph_docker_registry_password: <token>

dashboard admin user: dashboard admin password:

node_exporter_container_image: registry.redhat.io/openshift4/ose-prometheus-

node-exporter:v4.1 grafana_admin_user: grafana admin password:

grafana_container_image: registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8 prometheus_container_image: registry.redhat.io/openshift4/ose-prometheus:4.1 alertmanager_container_image: registry.redhat.io/openshift4/ose-prometheusalertmanager:4.1



IMPORTANT

Starting with Red Hat Ceph Storage 4.1, you must uncomment or set dashboard_admin_password and grafana_admin_password in /usr/share/ceph-ansible/group_vars/all.yml. Set secure passwords for each. Also set custom user names for dashboard_admin_user and grafana_admin_user.

ii. Bare-metal example of the all.yml file for ISO installation:

fetch directory: ~/ceph-ansible-keys

ceph_origin: repository ceph_repository: rhcs ceph_repository_type: iso

ceph_rhcs_iso_path: /home/rhceph-4-rhel-8-x86_64.iso

ceph_rhcs_version: 4

bootstrap_dirs_owner: "167" bootstrap_dirs_group: "167" monitor_interface: eth0 1 public network: 192.168.0.0/24 ceph_docker_registry: registry.redhat.io ceph_docker_registry_auth: true ceph_docker_registry_username: <service-account-user-name> ceph_docker_registry_password: <token> dashboard_admin_user: dashboard_admin_password: node_exporter_container_image: registry.redhat.io/openshift4/ose-prometheusnode-exporter:v4.1 grafana admin user: grafana_admin_password: grafana container image: registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8 prometheus_container_image: registry.redhat.io/openshift4/ose-prometheus:4.1 alertmanager_container_image: registry.redhat.io/openshift4/ose-prometheusalertmanager:4.1

This is the interface on the public network.

iii. Containers example of the all.yml file:

fetch directory: ~/ceph-ansible-keys monitor_interface: eth0 1 public network: 192.168.0.0/24 ceph docker image: rhceph/rhceph-4-rhel8 containerized deployment: true ceph_docker_registry: registry.redhat.io ceph docker registry auth: true ceph_docker_registry_username: <service-account-user-name> ceph_docker_registry_password: <token> ceph_origin: repository ceph_repository: rhcs ceph_repository_type: cdn ceph_rhcs_version: 4 bootstrap_dirs_owner: "167" bootstrap_dirs_group: "167" dashboard admin user: dashboard_admin_password: node_exporter_container_image: registry.redhat.io/openshift4/ose-prometheusnode-exporter:v4.1 grafana admin user: grafana admin password: grafana_container_image: registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8 prometheus_container_image: registry.redhat.io/openshift4/ose-prometheus:4.1 alertmanager_container_image: registry.redhat.io/openshift4/ose-prometheusalertmanager:4.1

1 This is the interface on the public network.



IMPORTANT

Starting with Red Hat Ceph Storage 4.1, you must uncomment or set dashboard_admin_password and grafana_admin_password in /usr/share/ceph-ansible/group_vars/all.yml. Set secure passwords for each. Also set custom user names for dashboard_admin_user and grafana_admin_user.

b. For all deployments, **bare-metal** or in **containers**, open for editing the **group vars/osds.yml** file.



IMPORTANT

Do not install an OSD on the device the operating system is installed on. Sharing the same device between the operating system and OSDs causes performance issues.

Ceph-ansible uses the **ceph-volume** tool to prepare storage devices for Ceph usage. You can configure **osds.yml** to use your storage devices in different ways to optimize performance for your particular workload.



IMPORTANT

All the examples below use the BlueStore object store, which is the format Ceph uses to store data on devices. Previously, Ceph used FileStore as the object store. This format is deprecated for new Red Hat Ceph Storage 4.0 installs because BlueStore offers more features and improved performance. It is still possible to use FileStore, but using it requires a Red Hat support exception. For more information on BlueStore, see Ceph BlueStore in the Red Hat Ceph Storage Architecture Guide.

i. Auto discovery

osd_auto_discovery: true

The above example uses all empty storage devices on the system to create the OSDs, so you do not have to specify them explicitly. The **ceph-volume** tool checks for empty devices, so devices which are not empty will not be used.

ii. Simple configuration

First Scenario

devices:

- /dev/sda
- /dev/sdb

or

Second Scenario

devices:

- /dev/sda

- /dev/sdb
- /dev/nvme0n1
- /dev/sdc
- /dev/sdd
- /dev/nvme1n1

or

Third Scenario

lvm_volumes:

data: /dev/sdbdata: /dev/sdc

or

Fourth Scenario

lvm_volumes:

- data: /dev/sdb

- data:/dev/nvme0n1

When using the **devices** option alone, **ceph-volume lvm batch** mode automatically optimizes OSD configuration.

In the first scenario, if the **devices** are traditional hard drives or SSDs, then one OSD per device is created.

In the second scenario, when there is a mix of traditional hard drives and SSDs, the data is placed on the traditional hard drives (**sda**, **sdb**) and the BlueStore database is created as large as possible on the SSD (**nvme0n1**). Similarly, the data is placed on the traditional hard drives (**sdc**, **sdd**), and the BlueStore database is created on the SSD **nvme1n1** irrespective of the order of devices mentioned.

In the third scenario, data is placed on the traditional hard drives (**sdb**, **sdc**), and the BlueStore database is collocated on the same devices.

In the fourth scenario, data is placed on the traditional hard drive (**sdb**) and on the SSD (**nvme1n1**), and the BlueStore database is collocated on the same devices. This is different from using the **devices** directive, where the BlueStore database is placed on the SSD.



IMPORTANT

The **ceph-volume lvm batch mode** command creates the optimized OSD configuration by placing data on the traditional hard drives and the BlueStore database on the SSD. If you want to specify the logical volumes and volume groups to use, you can create them directly by following the *Advanced configuration* scenarios below.

iii. Advanced configuration

First Scenario

devices:

- /dev/sda
- /dev/sdb

dedicated_devices:

- /dev/sdx
- /dev/sdy

or

Second Scenario

devices:

- /dev/sda
- /dev/sdb

dedicated devices:

- /dev/sdx
- /dev/sdy

bluestore_wal_devices:

- /dev/nvme0n1
- /dev/nvme0n2

In the first scenario, there are two OSDs. The **sda** and **sdb** devices each have their own data segments and write-ahead logs. The additional dictionary **dedicated_devices** is used to isolate their databases, also known as **block.db**, on **sdx** and **sdy**, respectively.

In the second scenario, another additional dictionary, **bluestore_wal_devices**, is used to isolate the write-ahead log on NVMe devices **nvme0n1** and **nvme0n2**. Using the **devices**, **dedicated_devices**, and **bluestore_wal_devices**, options together, this allows you to isolate all components of an OSD onto separate devices. Laying out the OSDs like this can increase overall performance.

iv. Pre-created logical volumes

First Scenario

lvm_volumes:

- data: data-lv1

data_vg: data-vg1

db: db-lv1

db_vg: db-vg1

wal: wal-lv1

wal_vg: wal-vg1

- data: data-lv2

data_vg: data-vg2

db: db-lv2

db_vg: db-vg2

wal: wal-lv2

wal_vg: wal-vg2

or

Second Scenario

lvm volumes:

data: /dev/sdbdb: db-lv1db_vg: db-vg1wal: wal-lv1wal_vg: wal-vg1

By default, Ceph uses Logical Volume Manager to create logical volumes on the OSD devices. In the *Simple configuration* and *Advanced configuration* examples above, Ceph creates logical volumes on the devices automatically. You can use previously created logical volumes with Ceph by specifying the **Ivm_volumes** dictionary.

In the first scenario, the data is placed on dedicated logical volumes, database, and WAL. You can also specify just data, data and WAL, or data and database. The **data**: line must specify the logical volume name where data is to be stored, and **data_vg**: must specify the name of the volume group the data logical volume is contained in. Similarly, **db**: is used to specify the logical volume the database is stored on and **db_vg**: is used to specify the volume group its logical volume is in. The **wal**: line specifies the logical volume the WAL is stored on and the **wal_vg**: line specifies the volume group that contains it.

In the second scenario, the actual device name is set for the **data:** option, and doing so, does not require specifying the **data_vg:** option. You must specify the logical volume name and the volume group details for the BlueStore database and WAL devices.



IMPORTANT

With **lvm_volumes:**, the volume groups and logical volumes must be created beforehand. The volume groups and logical volumes will not be created by **ceph-ansible**.



NOTE

If using all NVMe SSDs, then set **osds_per_device: 2**. For more information, see *Configuring OSD Ansible settings for all NVMe Storage* in the *Red Hat Ceph Storage Installation Guide*.



NOTE

After rebooting a Ceph OSD node, there is a possibility that the block device assignments will change. For example, **sdc** might become **sdd**. You can use persistent naming devices, such as the /**dev/disk/by-path/** device path, instead of the traditional block device name.

6. For all deployments, **bare-metal** or in **containers**, create the Ansible inventory file and then open it for editing:

[root@admin ~]# cd /usr/share/ceph-ansible/ [root@admin ceph-ansible]# touch hosts

Edit the **hosts** file accordingly.



NOTE

For information about editing the Ansible inventory location, see *Configuring the Ansible inventory location*.

a. Add a node under **[grafana-server]**. This role installs Grafana and Prometheus to provide real-time insights into the performance of the Ceph cluster. These metrics are presented in the Ceph Dashboard, which allows you to monitor and manage the cluster. The installation of the dashboard, Grafana, and Prometheus are required. You can colocate the metrics functions on the Ansible Administration node. If you do, ensure the system resources of the node are greater than than what is required for a stand alone metrics node.

```
[grafana-server]

GRAFANA-SERVER_NODE_NAME
```

b. Add the monitor nodes under the **[mons]** section:

```
[mons]

MONITOR_NODE_NAME_1

MONITOR_NODE_NAME_2

MONITOR_NODE_NAME_3
```

c. Add OSD nodes under the **[osds]** section:

```
[osds]

OSD_NODE_NAME_1

OSD_NODE_NAME_2

OSD_NODE_NAME_3
```



NOTE

You can add a range specifier ([1:10]) to the end of the node name, if the node names are numerically sequential. For example:

[osds] example-node[1:10]



NOTE

For OSDs in a new installation, the default object store format is BlueStore.

- d. Optionally, in container deployments, colocate Ceph Monitor daemons with the Ceph OSD daemons on one node by adding the same node under the [mon] and [osd] sections. See the link on colocating Ceph daemons in the Additional Resources section below for more information.
- e. Add the Ceph Manager (**ceph-mgr**) nodes under the **[mgrs]** section. This is colocating the Ceph Manager daemon with Ceph Monitor daemon.

```
[mgrs]
MONITOR_NODE_NAME_1
MONITOR_NODE_NAME_2
MONITOR_NODE_NAME_3
```

- 7. Optionally, if you want to use host specific parameters, for all deployments, **bare-metal** or in **containers**, create the **host_vars** directory with host files to include any parameters specific to hosts.
 - a. Create the **host_vars** directory:

\$ mkdir /usr/share/ceph-ansible/host_vars

b. In the **host_vars** directory, create host files. Use the *host-name-short-name* format for the name of the files, for example:

\$ touch tower-osd6

- c. Update the file with any host specific parameters, for example:
 - i. In bare-metal deployments use the devices parameter to specify devices that the OSD nodes will use. Using devices is useful when OSDs use devices with different names or when one of the devices failed on one of the OSDs.

devices: DEVICE_1 DEVICE_2

Example

devices: /dev/sdb /dev/sdc



NOTE

When specifying no devices, set the **osd_auto_discovery** parameter to **true** in the **osds.yml** file.

ii. For all deployments, bare-metal or in containers, if you want Ansible to create a custom CRUSH hierarchy, specify where you want the OSD hosts to be in the CRUSH map's hierarchy by using the osd_crush_location parameter in a specific host file. You must specify at least two CRUSH bucket types to specify the location of the OSD, and one bucket type must be host. By default, these include root, datacenter, room, row, pod, pdu, rack, chassis and host.

osd_crush_location: root: ROOT_BUCKET rack: RACK_BUCKET pod: POD_BUCKET

host: CEPH_NODE_NAME

Example

osd_crush_location: root: my-root rack: my-rack pod: my-pod host: tower-osd6

- 8. For all deployments, bare-metal or in containers, log in with or switch to the ansible user.
 - a. Create the **ceph-ansible-keys** directory where Ansible stores temporary values generated by the **ceph-ansible** playbook:
 - [ansible@admin ~]\$ mkdir ~/ceph-ansible-keys
 - b. Verify that Ansible can reach the Ceph nodes:
 - [ansible@admin ~]\$ ansible all -m ping -i hosts
 - c. Change to the /usr/share/ceph-ansible/ directory:
 - [ansible@admin ~]\$ cd /usr/share/ceph-ansible/
- 9. Run the ceph-ansible playbook.
 - a. Bare-metal deployments:
 - [ansible@admin ceph-ansible]\$ ansible-playbook site.yml -i hosts
 - b. Container deployments:
 - [ansible@admin ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts



NOTE

If you deploy Red Hat Ceph Storage to Red Hat Enterprise Linux Atomic Host hosts, use the **--skip-tags=with_pkg** option:

[user@admin ceph-ansible]\$ ansible-playbook site-docker.yml --skip-tags=with_pkg -i hosts



NOTE

To increase the deployment speed, use the **--forks** option to **ansible-playbook**. By default, **ceph-ansible** sets forks to **20**. With this setting, up to twenty nodes will be installed at the same time. To install up to thirty nodes at a time, run **ansible-playbook --forks 30 PLAYBOOK FILE -i hosts**. The resources on the admin node must be monitored to ensure they are not overused. If they are, lower the number passed to **--forks**.

- 10. Wait for the Ceph deployment to finish.
- 11. Verify the status of the Ceph storeage cluster.
 - a. Bare-metal deployments:

[root@monitor ~]# ceph health HEALTH_OK

b. Container deployments:

Red Hat Enterprise Linux 7

[root@ocp ~]# docker exec ceph-mon-ID ceph health

Red Hat Enterprise Linux 8

[root@ocp ~]# podman exec ceph-mon-ID ceph health

Replace

• **ID** with the host name of the Ceph Monitor node:

Example

[root@ocp ~]# podman exec ceph-mon-mon0 ceph health HEALTH_OK

- 12. For all deployments, **bare-metal** or in **containers**, verify the storage cluster is functioning using **rados**.
 - a. From a Ceph Monitor node, create a test pool with eight placement groups (PG):

Syntax

[root@mon ~]# ceph osd pool create POOL_NAME PG_NUMBER

Example

[root@mon ~]# ceph osd pool create test 8

b. Create a file called hello-world.txt:

Syntax

[root@monitor ~]# vim FILE_NAME

Example

[root@monitor ~]# vim hello-world.txt

c. Upload **hello-world.txt** to the test pool using the object name **hello-world**:

Syntax

[root@monitor ~]# rados --pool POOL_NAME put OBJECT_NAME OBJECT_FILE_NAME

Example

[root@monitor ~]# rados --pool test put hello-world hello-world.txt

d. Download **hello-world** from the test pool as file name **fetch.txt**:

Syntax

[root@monitor ~]# rados --pool POOL_NAME get OBJECT_NAME OBJECT_FILE_NAME

Example

[root@monitor ~]# rados --pool test get hello-world fetch.txt

e. Check the contents of fetch.txt:

[root@monitor ~]# cat fetch.txt "Hello World!"



NOTE

In addition to verifying the storage cluster status, you can use the **ceph-medic** utility to overall diagnose the Ceph Storage cluster. See the *Installing* and Using **ceph-medic** to Diagnose a Ceph Storage Cluster chapter in the Red Hat Ceph Storage 4 Troubleshooting Guide.

Additional Resources

- List of the common Ansible settings.
- List of the common OSD settings.
- See Colocation of containerized Ceph daemons for details.

4.3. CONFIGURING OSD ANSIBLE SETTINGS FOR ALL NVME STORAGE

To increase overall performance, you can configure Ansible to use only non-volatile memory express (NVMe) devices for storage. Normally only one OSD is configured per device, which underutilizes the throughput potential of an NVMe device.



NOTE

If you mix SSDs and HDDs, then SSDs will be used for the database, or **block.db**, not for data in OSDs.



NOTE

In testing, configuring two OSDs on each NVMe device was found to provide optimal performance. Red Hat recommends setting the **osds_per_device** option to **2**, but it is not required. Other values might provide better performance in your environment.

Prerequisites

- Access to an Ansible administration node.
- Installation of the **ceph-ansible** package.

Procedure

1. Set osds_per_device: 2 in group_vars/osds.yml:

osds_per_device: 2

2. List the NVMe devices under devices:

devices:

- /dev/nvme0n1
- /dev/nvme1n1
- /dev/nvme2n1
- /dev/nvme3n1
- 3. The settings in **group vars/osds.yml** will look similar to this example:

osds_per_device: 2

devices:

- /dev/nvme0n1
- /dev/nvme1n1
- /dev/nvme2n1
- /dev/nvme3n1



NOTE

You must use **devices** with this configuration, not **lvm_volumes**. This is because **lvm_volumes** is generally used with pre-created logical volumes and **osds_per_device** implies automatic logical volume creation by Ceph.

Additional Resources

• See the *Installing a Red Hat Ceph Storage Cluster* in the *Red Hat Ceph Storage Installation Guide* for more details.

4.4. INSTALLING METADATA SERVERS

Use the Ansible automation application to install a Ceph Metadata Server (MDS). Metadata Server daemons are necessary for deploying a Ceph File System.

Prerequisites

• A working Red Hat Ceph Storage cluster.

Procedure

Perform the following steps on the Ansible administration node.

1. Add a new section [mdss] to the /etc/ansible/hosts file:

```
[mdss]
NODE_NAME
NODE_NAME
NODE_NAME
```

Replace NODE_NAME with the host names of the nodes where you want to install the Ceph Metadata servers.

Alternatively, you can colocate the Metadata server with the OSD daemon on one node by adding the same node under the **[osds]** and **[mdss]** sections.

- 2. Navigate to the /usr/share/ceph-ansible directory:
 - [root@admin ~]# cd /usr/share/ceph-ansible
- 3. Optionally, you can change the default variables.
 - a. Create a copy of the **group_vars/mdss.yml.sample** file named **mdss.yml**:
 - [root@admin ceph-ansible]# cp group_vars/mdss.yml.sample group_vars/mdss.yml
 - b. Optionally, edit the parameters in **mdss.yml**. See **mdss.yml** for details.
- 4. As the **ansible** user, run the Ansible playbook:
 - Bare-metal deployments:
 - [user@admin ceph-ansible]\$ ansible-playbook site.yml --limit mdss -i hosts
 - Container deployments:
 - [ansible@admin ceph-ansible]\$ ansible-playbook site-docker.yml --limit mdss -i hosts
- 5. After installing the Metadata servers, you can now configure them. For details, see the *Configuring Metadata Server Daemons* chapter in the Ceph File System Guide.

Additional Resources

- The Ceph File System Guide for Red Hat Ceph Storage 4
- See Colocation of containerized Ceph daemons for details.
- See Understanding the limit option for details.

4.5. INSTALLING THE CEPH CLIENT ROLE

The **ceph-ansible** utility provides the **ceph-client** role that copies the Ceph configuration file and the administration keyring to nodes. In addition, you can use this role to create custom pools and clients.

Prerequisites

- A running Ceph storage cluster, preferably in the active + clean state.
- Perform the tasks listed in requirements.

Procedure

Perform the following tasks on the Ansible administration node.

1. Add a new section [clients] to the /etc/ansible/hosts file:

```
[clients] CLIENT_NODE_NAME
```

Replace *CLIENT_NODE_NAME* with the host name of the node where you want to install the **ceph-client** role.

- 2. Navigate to the /usr/share/ceph-ansible directory:
 - [root@admin ~]# cd /usr/share/ceph-ansible
- 3. Create a new copy of the **clients.yml.sample** file named **clients.yml**:
 - [root@admin ceph-ansible ~]# cp group_vars/clients.yml.sample group_vars/clients.yml
- 4. Open the **group_vars/clients.yml** file, and uncomment the following lines:

```
keys:
```

- { name: client.test, caps: { mon: "allow r", osd: "allow class-read object_prefix rbd_children, allow rwx pool=test" }, mode: "{{ ceph_keyring_permissions }}" }
- a. Replace **client.test** with the real client name, and add the client key to the client definition line, for example:

```
key: "ADD-KEYRING-HERE=="
```

Now the whole line example would look similar to this:

- { name: client.test, key: "AQAin8tUMICVFBAALRHNrV0Z4MXupRw4v9JQ6Q==", caps: { mon: "allow r", osd: "allow class-read object_prefix rbd_children, allow rwx pool=test" }, mode: "{{ ceph_keyring_permissions }}" }



NOTE

The **ceph-authtool --gen-print-key** command can generate a new client key.

- 5. Optionally, instruct **ceph-client** to create pools and clients.
 - a. Update clients.yml.

- Uncomment the **user_config** setting and set it to **true**.
- Uncomment the **pools** and **keys** sections and update them as required. You can define custom pools and client names altogether with the **cephx** capabilities.
- b. Add the osd_pool_default_pg_num setting to the ceph_conf_overrides section in the all.yml file:

```
ceph_conf_overrides:
  global:
  osd_pool_default_pg_num: NUMBER
```

Replace NUMBER with the default number of placement groups.

- 6. As the **ansible** user, run the Ansible playbook:
 - a. Bare-metal deployments:

[ansible@admin ceph-ansible]\$ ansible-playbook site.yml --limit clients -i hosts

b. Container deployments:

[ansible@admin ceph-ansible]\$ ansible-playbook site-docker.yml --limit clients -i hosts

Additional Resources

• See Understanding the limit option for details.

4.6. INSTALLING THE CEPH OBJECT GATEWAY

The Ceph Object Gateway, also know as the RADOS gateway, is an object storage interface built on top of the **librados** API to provide applications with a RESTful gateway to Ceph storage clusters.

Prerequisites

- A running Red Hat Ceph Storage cluster, preferably in the **active + clean** state.
- On the Ceph Object Gateway node, perform the tasks listed in Chapter 2, Requirements for Installing Red Hat Ceph Storage.



WARNING

If you intend to use Ceph Object Gateway in a multisite configuration, only complete steps 1 - 7. Do not run the Ansible playbook before configuring multisite as this will start the Object Gateway in a single site configuration. Ansible cannot reconfigure the gateway to a multisite setup after it has already been started in a single site configuration. After you complete steps 1-7, proceed to the Configuring multisite Ceph Object Gateways section to set up multisite.

Procedure

Perform the following tasks on the Ansible administration node.

1. Add gateway hosts to the /etc/ansible/hosts file under the [rgws] section to identify their roles to Ansible. If the hosts have sequential naming, use a range, for example:

```
[rgws]
<rgw_host_name_1>
<rgw_host_name_2>
<rgw_host_name[3..10]>
```

- 2. Navigate to the Ansible configuration directory:
 - [root@ansible ~]# cd /usr/share/ceph-ansible
- 3. Create the **rgws.yml** file from the sample file:
 - [root@ansible ~]# cp group_vars/rgws.yml.sample group_vars/rgws.yml
- 4. Open and edit the **group_vars/rgws.yml** file. To copy the administrator key to the Ceph Object Gateway node, uncomment the **copy_admin_key** option:

```
copy_admin_key: true
```

5. In the all.yml file, you MUST specify a radosgw interface.

```
radosgw_interface: <interface>
```

Replace:

<interface> with the interface that the Ceph Object Gateway nodes listen to

For example:

```
radosgw_interface: eth0
```

Specifying the interface prevents Civetweb from binding to the same IP address as another Civetweb instance when running multiple instances on the same host.

For additional details, see the all.yml file.

6. Generally, to change default settings, uncomment the settings in the rgws.yml file, and make changes accordingly. To make additional changes to settings that are not in the rgws.yml file, use ceph_conf_overrides: in the all.yml file. For example, set the rgw_dns_name: with the host of the DNS server and ensure the cluster's DNS server to configure it for wild cards to enable S3 subdomains.

```
ceph_conf_overrides:
  client.rgw.rgw1:
    rgw_dns_name: <host_name>
    rgw_override_bucket_index_max_shards: 16
    rgw_bucket_default_quota_max_objects: 1638400
```

For advanced configuration details, see the Red Hat Ceph Storage 4 Ceph Object Gateway for Production guide. Advanced topics include:

- Configuring Ansible Groups
- Developing Storage Strategies. See the Creating the Root Pool, Creating System Pools, and Creating Data Placement Strategies sections for additional details on how create and configure the pools.

See Bucket Sharding for configuration details on bucket sharding.

7. Run the Ansible playbook:



WARNING

Do not run the Ansible playbook if you intend to set up multisite. Proceed to the Configuring multisite Ceph Object Gateways section to set up multisite.

- a. Bare-metal deployments:
 - [user@admin ceph-ansible]\$ ansible-playbook site.yml --limit rgws -i hosts
- b. Container deployments:
 - [user@admin ceph-ansible]\$ ansible-playbook site-docker.yml --limit rgws -i hosts



NOTE

Ansible ensures that each Ceph Object Gateway is running.

For a single site configuration, add Ceph Object Gateways to the Ansible configuration.

For multi-site deployments, you should have an Ansible configuration for each zone. That is, Ansible will create a Ceph storage cluster and gateway instances for that zone.

After installation for a multi-site cluster is complete, proceed to the Multi-site chapter in the Red Hat Ceph Storage 4 *Object Gateway Guide* for details on configuring a cluster for multi-site.

Additional Resources

- Section 4.10, "Understanding the **limit** option"
- The Red Hat Ceph Storage 4 Object Gateway Guide

4.7. CONFIGURING MULTISITE CEPH OBJECT GATEWAYS

As a system administrator, you can configure multisite Ceph Object Gateways to mirror data across clusters for disaster recovery purposes.

You can configure multisite with one or more RGW realms. A realm allows the RGWs inside of it to be independent and isolated from RGWs outside of the realm. This way, data written to an RGW in one realm cannot be accessed by an RGW in another realm.



WARNING

Do not use Ansible to configure multisite Ceph Object Gateways on clusters with existing single site Ceph Object Gateways. Ansible cannot reconfigure gateways to a multisite setup after they have already been started in single site configurations.



NOTE

From Red Hat Ceph Storage 4.1, you do not need to set the value of **rgw_multisite_endpoints_list** in **group_vars/all.yml** file.

4.7.1. Prerequisites

- Two Red Hat Ceph Storage clusters.
- On the Ceph Object Gateway nodes, perform the tasks listed in the *Requirements for Installing Red Hat Ceph Storage* found in the *Red Hat Ceph Storage Installation Guide*.
- For each Object Gateway node, perform steps 1 7 in Installing the Ceph Object Gateway.

4.7.2. Configuring a multisite Ceph Object Gateway with one realm

Ansible will configure Ceph Object Gateways to mirror data in one realm across multiple clusters.



WARNING

Do not use Ansible to configure multisite Ceph Object Gateways on clusters with existing single site Ceph Object Gateways. Ansible cannot reconfigure gateways to a multisite setup after they have already been started in single site configurations.

Prerequisites

- Two running Red Hat Ceph Storage clusters.
- On the Ceph Object Gateway nodes, perform the tasks listed in the Requirements for Installing Red Hat Ceph Storage found in the Red Hat Ceph Storage Installation Guide.
- For each Object Gateway node, perform steps 1 7 in Installing the Ceph Object Gateway.

Procedure

- 1. Do the following steps on Ansible node for the primary storage cluster:
 - a. Generate the system keys and capture their output in the **multi-site-keys.txt** file:

```
[root@ansible \sim]# echo system_access_key: $(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 20 | head -n 1) > multi-site-keys.txt [root@ansible \sim]# echo system_secret_key: $(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 40 | head -n 1) >> multi-site-keys.txt
```

b. Navigate to the Ansible configuration directory, /usr/share/ceph-ansible:

[root@ansible ~]# cd /usr/share/ceph-ansible

c. Open and edit the **group_vars/all.yml** file. Configure the following settings, along with updating the ZONE_NAME, ZONE_GROUP_NAME, ZONE_USER_NAME, ZONE_DISPLAY_NAME, and REALM_NAME accordingly. Use the random strings saved in the **multi-site-keys.txt** file for ACCESS_KEY and SECRET_KEY.

Syntax

```
rgw_multisite: true
rgw_zone: ZONE_NAME
rgw_zonegroup: ZONE_GROUP_NAME
rgw_realm: REALM_NAME
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: ZONE_USER_NAME
rgw_zone_user_display_name: ZONE_DISPLAY_NAME
system_access_key: ACCESS_KEY
system_secret_key: SECRET_KEY
rgw_multisite_proto: "http"
```

Example

```
rgw_multisite: true
rgw_zone: juneau
rgw_zonegroup: alaska
rgw_realm: usa
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: synchronization-user
rgw_zone_user_display_name: "Synchronization User"
rgw_multisite_proto: "http"
system_access_key: 86nBoQOGpQgKxh4BLMyq
system_secret_key: NTnkbmkMuzPjgwsBpJ6o
```

d. Run the Ansible playbook:

 $[ansible@ansible\ ceph-ansible]\$\ ansible-playbook\ site.yml$

2. Do the following steps on the Ansible node for the secondary storage cluster:

a. Navigate to the Ansible configuration directory, /usr/share/ceph-ansible:

[root@ansible ~]# cd /usr/share/ceph-ansible

b. Open and edit the **group_vars/all.yml** file. Configure the following settings. Use the same values as used on the first cluster for *ZONE_USER_NAME*, *ZONE_DISPLAY_NAME*, *ACCESS_KEY*, *SECRET_KEY*, *REALM_NAME*, and *ZONE_GROUP_NAME*. Use a different value for *ZONE_NAME* from the first cluster. Set *MASTER_RGW_NODE_NAME* to the Ceph Object Gateway node for the master zone. Note that, compared to the first cluster, the settings for **rgw_zonemaster** and **rgw_zonesecondary** are reversed.

Syntax

```
rgw_multisite: true
rgw_zone: ZONE_NAME
rgw_zonegroup: ZONE_GROUP_NAME
rgw_realm: REALM_NAME
rgw_zonemaster: false
rgw_zonesecondary: true
rgw_zonegroupmaster: true
rgw_zone_user: ZONE_USER_NAME
rgw_zone_user_display_name: ZONE_DISPLAY_NAME
system_access_key: ACCESS_KEY
system_secret_key: SECRET_KEY
rgw_multisite_proto: "http"
rgw_pull_proto: http
rgw_pull_port: 8080
rgw_pullhost: MASTER_RGW_NODE_NAME
```

Example

```
rgw_multisite: true
rgw_zone: fairbanks
rgw_zonegroup: alaska
rgw_realm: usa
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: synchronization-user
rgw_zone_user_display_name: "Synchronization User"
system_access_key: 86nBoQOGpQgKxh4BLMyq
system_secret_key: NTnkbmkMuzPjgwsBpJ6o
rgw_multisite_proto: "http"
rgw_pull_proto: http
rgw_pull_port: 8080
rgw_pullhost: cluster0-rgw-000
```

- 3. Run the Ansible playbook on the primary cluster
 - a. Bare-metal deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site.yml -i hosts

b. Container deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts

- 4. Verify the secondary cluster can access the API on the primary cluster. From the Object Gateway nodes on the secondary cluster, use **curl** or another HTTP client to connect to the API on the primary cluster. Compose the URL using the information used to configure **rgw_pull_proto**, **rgw_pullhost**, and **rgw_pull_port** in **all.yml**. Following the example above, the URL is http://cluster0-rgw-000:8080. If you cannot access the API, verify the URL is right and update **all.yml** if required. Once the URL works and any network issues are resolved, continue with the next step to run the Ansible playbook on the secondary cluster.
- 5. Run the Ansible playbook on the secondary cluster
 - a. Bare-metal deployments:
 - [user@ansible ceph-ansible]\$ ansible-playbook site.yml -i hosts
 - b. Container deployments:
 - [user@ansible ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts

After running the Ansible playbook on the master and secondary storage clusters, the Ceph Object Gateways run in an active-active state.

- 6. Verify the multisite Ceph Object Gateway configuration:
 - a. From the Ceph Monitor and Object Gateway nodes at each site, primary and secondary, use **curl** or another HTTP client to verify the API is accessible from the other site.
 - b. Run the **radosgw-admin sync status** command on both sites.

4.7.3. Configuring a multisite Ceph Object Gateway with multiple realms

Ansible will configure Ceph Object Gateways to mirror data in multiple realms across multiple clusters.



WARNING

Do not use Ansible to configure multisite Ceph Object Gateways on clusters with existing single site Ceph Object Gateways. Ansible cannot reconfigure gateways to a multisite setup after they have already been started in single site configurations.

Prerequisites

- Two running Red Hat Ceph Storage clusters.
- At least two Object Gateway nodes in each cluster.
- On the Ceph Object Gateway nodes, perform the tasks listed in the Requirements for Installing Red Hat Ceph Storage found in the Red Hat Ceph Storage Installation Guide.
- For each Object Gateway node, perform steps 1 7 in Installing the Ceph Object Gateway.

Procedure

1. On any node, generate the system access keys and secret keys for realm one and two, and save them in files named **multi-site-keys-realm-1.txt** and **multi-site-keys-realm-2.txt**, respectively:

```
# echo system_access_key: $(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 20 | head -n 1) >
multi-site-keys-realm-1.txt
[root@ansible ~]# echo system_secret_key: $(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w
40 | head -n 1) >> multi-site-keys-realm-1.txt

# echo system_access_key: $(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 20 | head -n 1) >
multi-site-keys-realm-2.txt
[root@ansible ~]# echo system_secret_key: $(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w
40 | head -n 1) >> multi-site-keys-realm-2.txt
```

- 2. Do the following steps on the Ansible node for the primary storage cluster:
 - a. Navigate to the Ansible configuration directory, /usr/share/ceph-ansible:

[root@ansible ~]# cd /usr/share/ceph-ansible

b. Create a host_vars directory in /usr/share/ceph-ansible

[root@ansible ceph-ansible]# mkdir host_vars

c. Open and edit the **group_vars/all.yml** file. Uncomment the **rgw_multisite** line and set it to **true**.

rgw_multisite: true

d. Create a file in **host_vars** for the first Object Gateway node on the primary cluster. The file name should be the same name as used in the Ansible inventory file. For example, if the first Object Gateway node is named **rgw-001**, create the file **host_vars/rgw-001**

touch host_vars/NODE_NAME

Example:

[root@ansible ceph-ansible]# touch host_vars/rgw-001

e. Open and edit the file, for example **host_vars/rgw-001**. Configure the following settings, along with updating the *ZONE_NAME_1*, *ZONE_GROUP_NAME_1*, *ZONE_USER_NAME_1*, *ZONE_DISPLAY_NAME_1*, and *REALM_NAME_1* accordingly. Use the random strings saved in the **multi-site-keys-realm-1.txt** file for *ACCESS_KEY_1* and *SECRET_KEY_1*.

Syntax

```
rgw_zone: ZONE_NAME_1
rgw_zonegroup: ZONE_GROUP_NAME_1
rgw_realm: REALM_NAME_1
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: ZONE_USER_NAME_1
```

```
rgw_zone_user_display_name: "ZONE_DISPLAY_NAME_1" system_access_key: ACCESS_KEY_1 system_secret_key: SECRET_KEY_1 rgw_multisite_proto: "http" radosgw_address: "{{ _radosgw_address }}" radosgw_frontend_port: 8080
```

Example

```
rgw_zone: paris
rgw_zonegroup: idf
rgw_realm: france
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: jacques.chirac
rgw_zone_user_display_name: "Jacques Chirac"
system_access_key: P9Eb6S8XNyo4dtZZUUMy
system_secret_key: qqHCUtfdNnpHq3PZRHW5un9l0bEBM812Uhow0XfB
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
```

f. Create a file in **host_vars** for the second Object Gateway node. The file should be the same name as used in the Ansible inventory file. For example, if the first Object Gateway node is named **rgw-002**, create the file **host_vars/rgw-002**

touch host_vars/NODE_NAME

Example:

[root@ansible ceph-ansible]# touch host_vars/rgw-002

g. Open and edit the file, for example **host_vars/rgw-002**. Configure the following settings, along with updating the *ZONE_NAME_2*, *ZONE_GROUP_NAME_2*, *ZONE_USER_NAME_2*, *ZONE_DISPLAY_NAME_2*, and *REALM_NAME_2* accordingly. Use the random strings saved in the **multi-site-keys-realm-2.txt** file for *ACCESS_KEY_2* and *SECRET_KEY_2*.

Syntax

```
rgw_zone: ZONE_NAME_2
rgw_zonegroup: ZONE_GROUP_NAME_2
rgw_realm: REALM_NAME_2
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: ZONE_USER_NAME_2
rgw_zone_user_display_name: ZONE_DISPLAY_NAME_2
system_access_key: ACCESS_KEY_2
system_secret_key: SECRET_KEY_2
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
```

Example

```
rgw_zone: juneau
rgw_zonegroup: alaska
rgw_realm: usa
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: edward.lewis
rgw_zone_user_display_name: "Edward Lewis"
system_access_key: yu17wkvAx3B8Wyn08XoF
system_secret_key: 5YZfaSUPqxSNIkZQQA3IBZ495hnIV6k2HAz710BY=
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
```

- 3. Run the Ansible playbook on the primary cluster:
 - a. Bare-metal deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site.yml -i hosts

b. Container deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts

- 4. Do the following steps on the Ansible node for the secondary storage cluster:
 - a. Navigate to the Ansible configuration directory, /usr/share/ceph-ansible:

[root@ansible ~]# cd /usr/share/ceph-ansible

b. Create a host vars directory in /usr/share/ceph-ansible

[root@ansible ceph-ansible]# mkdir host_vars

c. Open and edit the **group_vars/all.yml** file. Uncomment the **rgw_multisite** line and set it to **true**.

rgw_multisite: true

d. Create a file in **host_vars** for the first Object Gateway node on the secondary cluster. The file name should be the same name as used in the Ansible inventory file. For example, if the first Object Gateway node in the secondary cluster is named **rgw-003**, create the file **host_vars/rgw-003**

touch host_vars/NODE_NAME

Example:

[root@ansible ceph-ansible]# touch host_vars/rgw-003

e. Open and edit the file, for example host_vars/rgw-003. Configure the following settings,

along with updating the ZONE_NAME_1, ZONE_GROUP_NAME_1, ZONE_USER_NAME_1, ZONE_DISPLAY_NAME_1, and REALM_NAME_1 accordingly. The PULLHOST_1 variable should be set to the hostname for the first Object Gateway node on the primary cluster. Use the random strings saved in the **multi-site-keys-realm-1.txt** file for ACCESS_KEY_1 and SECRET_KEY_1. Note that, compared to the first cluster, the settings for **rgw_zonemaster** and **rgw_zonesecondary** are reversed.

Syntax

```
rgw zone: ZONE NAME 1
rgw_zonegroup: ZONE_GROUP_NAME_1
rgw_realm: REALM_NAME_1
rgw zonemaster: false
rgw zonesecondary: true
rgw_zonegroupmaster: true
rgw_zone_user: ZONE_USER_NAME_1
rgw_zone_user_display_name: "ZONE_DISPLAY_NAME_1"
system access key: ACCESS KEY 1
system_secret_key: SECRET_KEY_1
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
rgw pull proto: http
rgw_pull_port: 8080
rgw_pullhost: PULLHOST_1
```

Example

```
rgw_zone: paris
rgw_zonegroup: idf
rgw_realm: france
rgw zonemaster: true
rgw zonesecondary: false
rgw_zonegroupmaster: true
rgw_zone_user: jacques.chirac
rgw zone user display name: "Jacques Chirac"
system_access_key: P9Eb6S8XNyo4dtZZUUMy
system_secret_key: qqHCUtfdNnpHq3PZRHW5un9l0bEBM812Uhow0XfB
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
rgw_pull_proto: http
rgw_pull_port: 8080
rgw_pullhost: rgw-001
```

f. Create a file in **host_vars** for the second Object Gateway node. The file should be the same name as used in the Ansible inventory file. For example, if the second Object Gateway node in the secondary cluster is named **rgw-004**, create the file **host vars/rgw-004**.

touch host_vars/NODE_NAME

Example:

[root@ansible ceph-ansible]# touch host vars/rgw-004

g. Open and edit the file, for example **host_vars/rgw-004** file. Configure the following settings, along with updating the *ZONE_NAME_2*, *ZONE_GROUP_NAME_2*, *ZONE_USER_NAME_2*, *ZONE_DISPLAY_NAME_2*, and *REALM_NAME_2* accordingly. The *PULLHOST_2* variable should be set to the hostname for the second Object Gateway node on the primary cluster. Use the random strings saved in the **multi-site-keys-realm-2.txt** file for *ACCESS_KEY_2* and *SECRET_KEY_2*. Note that, compared to the first cluster, the settings for **rgw_zonemaster** and **rgw_zonesecondary** are reversed.

Syntax

```
rgw_zone: ZONE_NAME_2
rgw_zonegroup: ZONE_GROUP_NAME_2
rgw_realm: REALM_NAME_2
rgw_zonemaster: false
rgw_zonesecondary: true
rgw_zonegroupmaster: true
rgw_zone_user: ZONE_USER_NAME_2
rgw_zone_user_display_name: ZONE_DISPLAY_NAME_2
system_access_key: ACCESS_KEY_2
system_secret_key: SECRET_KEY_2
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
rgw_pullhost: PULLHOST_2
```

Example

```
rgw_zone: juneau
rgw_zonegroup: alaska
rgw_realm: usa
rgw_zonemaster: false
rgw_zonesecondary: true
rgw_zonegroupmaster: true
rgw_zone_user: edward.lewis
rgw_zone_user_display_name: "Edward Lewis"
system_access_key: yu17wkvAx3B8Wyn08XoF
system_secret_key: 5YZfaSUPqxSNlkZQQA3lBZ495hnlV6k2HAz710BY=
rgw_multisite_proto: "http"
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
rgw_pull_port: 8080
rgw_pullhost: rgw-002
```

- 5. Run the Ansible playbook on the secondary cluster:
 - a. Bare-metal deployments:
 - [user@ansible ceph-ansible]\$ ansible-playbook site.yml -i hosts
 - b. Container deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts

After running the Ancible playbook on the primary and eccendary storage clusters, the Conh

After running the Ansible playbook on the primary and secondary storage clusters, the Cephi Object Gateways run in an active-active state.

- 6. Verify the multisite Ceph Object Gateway configuration:
 - a. From the Ceph Monitor and Object Gateway nodes at each site, primary and secondary, use **curl** or another HTTP client to verify the APIs are accessible from the other site.
 - b. Run the radosgw-admin sync status command on both sites.

4.7.4. Configuring a multisite Ceph Object Gateway with multiple realms and multiple RGW instances

Ansible will configure Ceph Object Gateways to mirror data in multiple realms across multiple clusters with multiple RGW instances.



WARNING

Do not use Ansible to configure multisite Ceph Object Gateways on clusters with existing single site Ceph Object Gateways. Ansible cannot reconfigure gateways to a multisite setup after they have already been started in single site configurations.

Prerequisites

- Two running Red Hat Ceph Storage clusters.
- One Object Gateway node in each cluster.
- On the Ceph Object Gateway nodes, perform the tasks listed in the Requirements for Installing Red Hat Ceph Storage found in the Red Hat Ceph Storage Installation Guide.
- For each Object Gateway node, perform steps 1 7 in Installing the Ceph Object Gateway.

Procedure

1. On any node, generate the system access keys and secret keys for realm one and two, and save them in files named **multi-site-keys-realm-1.txt** and **multi-site-keys-realm-2.txt**, respectively:

echo system_access_key: \$(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 20 | head -n 1) > multi-site-keys-realm-1.txt

[root@ansible ~]# echo system_secret_key: \$(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 40 | head -n 1) >> multi-site-keys-realm-1.txt

echo system_access_key: (cat / dev / urandom | tr - dc 'a-zA-Z0-9' | fold -w 20 | head -n 1) > multi-site-keys-realm-2.txt

[root@ansible ~]# echo system_secret_key: \$(cat /dev/urandom | tr -dc 'a-zA-Z0-9' | fold -w 40 | head -n 1) >> multi-site-keys-realm-2.txt

- 2. Do the following steps on the Ansible node for the primary storage cluster:
 - a. Navigate to the Ansible configuration directory, /usr/share/ceph-ansible:

[root@ansible ~]# cd /usr/share/ceph-ansible

b. Create a host vars directory in /usr/share/ceph-ansible

[root@ansible ceph-ansible]# mkdir host_vars

c. Open and edit the **group_vars/all.yml** file. Uncomment the **rgw_multisite** line and set it to **true**.

```
rgw_multisite: true
```

d. Create a file in **host_vars** for the Object Gateway node on the primary cluster. The file name should be the same name as used in the Ansible inventory file. For example, if the Object Gateway node is named **rgw-primary**, create the file **host_vars/rgw-primary**

```
touch host_vars/NODE_NAME
```

Example:

[root@ansible ceph-ansible]# touch host_vars/rgw-primary

e. Open and edit the file, for example **host_vars/rgw-primary**. Configure the settings that apply to all instances on the primary cluster:

```
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_multisite_proto: "http"
rgw_instances:
```

f. Add an item under **rgw_instances** for the first realm. Configure the following settings, along with updating the *INSTANCE_NAME_1*, *ZONE_NAME_1*, *ZONE_GROUP_NAME_1*, *ZONE_USER_NAME_1*, *ZONE_DISPLAY_NAME_1*, and *REALM_NAME_1* accordingly. Use the random strings saved in the **multi-site-keys-realm-1.txt** file for *ACCESS_KEY_1* and *SECRET_KEY_1*.

Syntax

```
- instance_name: INSTANCE_NAME_1
rgw_zone: ZONE_NAME_1
rgw_zonegroup: ZONE_GROUP_NAME_1
rgw_realm: REALM_NAME_1
rgw_zone_user: ZONE_USER_NAME_1
rgw_zone_user_display_name: "ZONE_DISPLAY_NAME_1"
system_access_key: ACCESS_KEY_1
system_secret_key: SECRET_KEY_1
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
```

Example

instance_name: rgw1

```
rgw_zone: paris
rgw_zonegroup: idf
rgw_realm: france
rgw_zone_user: jacques.chirac
rgw_zone_user_display_name: "Jacques Chirac"
system_access_key: P9Eb6S8XNyo4dtZZUUMy
system_secret_key: qqHCUtfdNnpHq3PZRHW5un9l0bEBM812Uhow0XfB
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
```

g. Add an item under **rgw_instances** for the second realm. Configure the following settings, along with updating the *INSTANCE_NAME_2*, ZONE_NAME_2, *ZONE_GROUP_NAME_2*, *ZONE_USER_NAME_2*, *ZONE_DISPLAY_NAME_2*, and *REALM_NAME_2* accordingly. Use the random strings saved in the **multi-site-keys-realm-2.txt** file for *ACCESS_KEY_2* and *SECRET_KEY_2*.

Syntax

```
- instance_name: INSTANCE_NAME_2
rgw_zone: ZONE_NAME_2
rgw_zonegroup: ZONE_GROUP_NAME_2
rgw_realm: REALM_NAME_2
rgw_zone_user: ZONE_USER_NAME_2
rgw_zone_user_display_name: "ZONE_DISPLAY_NAME_2"
system_access_key: ACCESS_KEY_2
system_secret_key: SECRET_KEY_2
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8081
```

Example

```
- instance_name: rgw2
  rgw_zone: juneau
  rgw_zonegroup: alaska
  rgw_realm: usa
  rgw_zone_user: edward.lewis
  rgw_zone_user_display_name: "Edward Lewis"
  system_access_key: yu17wkvAx3B8Wyn08XoF
  system_secret_key: 5YZfaSUPqxSNIkZQQA3IBZ495hnIV6k2HAz710BY=
  radosgw_address: "{{ _radosgw_address }}"
  radosgw_frontend_port: 8081
```

h. Verify the complete **host vars** file for the primary gateway looks like this example:

```
rgw_zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_multisite_proto: "http"
rgw_instances:
- instance_name: rgw1
rgw_zone: paris
rgw_zonegroup: idf
rgw_realm: france
rgw_zone_user: jacques.chirac
rgw_zone_user_display_name: "Jacques Chirac"
```

system_access_key: P9Eb6S8XNyo4dtZZUUMy
system_secret_key: qqHCUtfdNnpHq3PZRHW5un9l0bEBM812Uhow0XfB
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
-instance_name: rgw2
rgw_zone: juneau
rgw_zonegroup: alaska
rgw_realm: usa
rgw_zone_user: edward.lewis
rgw_zone_user_display_name: "Edward Lewis"
system_access_key: yu17wkvAx3B8Wyn08XoF
system_secret_key: 5YZfaSUPqxSNIkZQQA3IBZ495hnIV6k2HAz710BY=

radosgw_address: "{{ _radosgw_address }}"

radosgw_frontend_port: 8081

- 3. Run the Ansible playbook on the primary cluster:
 - a. Bare-metal deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site.yml -i hosts

b. Container deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts

- 4. Do the following steps on the Ansible node for the secondary storage cluster:
 - a. Navigate to the Ansible configuration directory, /usr/share/ceph-ansible:

[root@ansible ~]# cd /usr/share/ceph-ansible

b. Create a host_vars directory in /usr/share/ceph-ansible

[root@ansible ceph-ansible]# mkdir host_vars

c. Open and edit the **group_vars/all.yml** file. Uncomment the **rgw_multisite** line and set it to **true**.

rgw_multisite: true

d. Create a file in **host_vars** for the Object Gateway node on the secondary cluster. The file name should be the same name as used in the Ansible inventory file. For example, if the Object Gateway node is named **rgw-secondary**, create the file **host_vars/rgw-secondary**

touch host_vars/NODE_NAME

Example:

[root@ansible ceph-ansible]# touch host_vars/rgw-secondary

e. Open and edit the file, for example **host_vars/rgw-secondary**. Configure the settings that apply to all instances on the secondary cluster:

```
rgw_zonemaster: false
rgw_zonesecondary: true
rgw_zonegroupmaster: true
rgw_multisite_proto: "http"
rgw_instances:
```

f. Add an item under **rgw_instances** for the first realm. Configure the following settings, along with updating the *INSTANCE_NAME_3*, *ZONE_NAME_1*, *ZONE_GROUP_NAME_1*, *ZONE_USER_NAME_1*, *ZONE_DISPLAY_NAME_1*, and *REALM_NAME_1* accordingly. Use the random strings saved in the **multi-site-keys-realm-1.txt** file for *ACCESS_KEY_1* and *SECRET_KEY_1*. Set *RGW_PRIMARY_HOSTNAME* to the Object Gateway node in the primary cluster.

Syntax

```
- instance_name: INSTANCE_NAME_3
rgw_zone: ZONE_NAME_1
rgw_zonegroup: ZONE_GROUP_NAME_1
rgw_realm: REALM_NAME_1
rgw_zone_user: ZONE_USER_NAME_1
rgw_zone_user_display_name: "ZONE_DISPLAY_NAME_1"
system_access_key: ACCESS_KEY_1
system_secret_key: SECRET_KEY_1
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
endpoint: http://RGW_PRIMARY_HOSTNAME:8080
```

Example

```
- instance_name: rgw3
rgw_zone: paris
rgw_zonegroup: idf
rgw_realm: france
rgw_zone_user: jacques.chirac
rgw_zone_user_display_name: "Jacques Chirac"
system_access_key: P9Eb6S8XNyo4dtZZUUMy
system_secret_key: qqHCUtfdNnpHq3PZRHW5un9I0bEBM812Uhow0XfB
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8080
endpoint: http://rgw-primary:8080
```

g. Add an item under **rgw_instances** for the second realm. Configure the following settings, along with updating the *INSTANCE_NAME_4*, ZONE_NAME_2, *ZONE_GROUP_NAME_2*, *ZONE_USER_NAME_2*, *ZONE_DISPLAY_NAME_2*, and *REALM_NAME_2* accordingly. Use the random strings saved in the **multi-site-keys-realm-2.txt** file for *ACCESS_KEY_2* and *SECRET_KEY_2*. Set *RGW_PRIMARY_HOSTNAME* to the Object Gateway node in the primary cluster.

Syntax

```
    instance_name: INSTANCE_NAME_4
    rgw_zone: ZONE_NAME_2
    rgw_zonegroup: ZONE_GROUP_NAME_2
    rgw_realm: REALM_NAME_2
```

```
rgw_zone_user: ZONE_USER_NAME_2
rgw_zone_user_display_name: "ZONE_DISPLAY_NAME_2"
system_access_key: ACCESS_KEY_2
system_secret_key: SECRET_KEY_2
radosgw_address: "{{ _radosgw_address }}"
radosgw_frontend_port: 8081
endpoint: http://RGW_PRIMARY_HOSTNAME:8081
```

Example

```
- instance_name: rgw4
  rgw_zone: juneau
  rgw_zonegroup: alaska
  rgw_realm: usa
  rgw_zone_user: edward.lewis
  rgw_zone_user_display_name: "Edward Lewis"
  system_access_key: yu17wkvAx3B8Wyn08XoF
  system_secret_key: 5YZfaSUPqxSNIkZQQA3IBZ495hnIV6k2HAz710BY=
  radosgw_address: "{{ _radosgw_address }}"
  radosgw_frontend_port: 8081
  endpoint: http://rgw-primary:8081
```

h. Verify the complete **host_vars** file for the secondary gateway looks like this example:

```
rgw zonemaster: true
rgw_zonesecondary: false
rgw_zonegroupmaster: true
rgw_multisite_proto: "http"
rgw_instances:
 - instance_name: rgw3
  rgw_zone: paris
  rgw_zonegroup: idf
  rgw_realm: france
  rgw_zone_user: jacques.chirac
  rgw_zone_user_display_name: "Jacques Chirac"
  system access key: P9Eb6S8XNyo4dtZZUUMy
  system_secret_key: qqHCUtfdNnpHq3PZRHW5un9l0bEBM812Uhow0XfB
  radosgw_address: "{{ _radosgw_address }}"
  radosgw frontend port: 8080
  endpoint: http://rgw-primary:8080
 - instance_name: rgw4
  rgw_zone: juneau
  rgw_zonegroup: alaska
  rgw_realm: usa
  rgw_zone_user: edward.lewis
  rgw_zone_user_display_name: "Edward Lewis"
  system_access_key: yu17wkvAx3B8Wyn08XoF
  system_secret_key: 5YZfaSUPqxSNlkZQQA3lBZ495hnlV6k2HAz710BY=
  radosgw address: "{{ radosgw address }}"
  radosgw frontend port: 8081
  endpoint: http://rgw-primary:8081
```

- 5. Run the Ansible playbook on the secondary cluster:
 - a. Bare-metal deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site.yml -i hosts

b. Container deployments:

[user@ansible ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts

After running the Ansible playbook on the primary and secondary storage clusters, the Ceph Object Gateways run in an active-active state.

- 6. Verify the multisite Ceph Object Gateway configuration:
 - a. From the Ceph Monitor and Object Gateway nodes at each site, primary and secondary, use **curl** or another HTTP client to verify the APIs are accessible from the other site.
 - b. Run the radosgw-admin sync status command on both sites.

4.8. DEPLOYING OSDS WITH DIFFERENT HARDWARE ON THE SAME HOST

You can deploy mixed OSDs, for example, HDDs and SSDs, on the same host, with the **device_class** feature in Ansible.

Prerequisites

- A valid customer subscription.
- Root-level access to Ansible Administration node.
- Enable Red Hat Ceph Storage Tools and Ansible repositories.
- The ansible user account for use with the Ansible application.
- OSDs are deployed.

Procedure

1. Create crush rules in the group vars/mons.yml file:

Example

```
create_crush_tree: true
crush_rule_config: true
crush_rules:
name: HDD
root: default
type: host
class: hdd
default: true
name: SDD
root: default
type: host
class: sdd
default: true
```



NOTE

If you are not using SDD or HDD devices in the cluster, do not define the **crush_rules** for that device.

2. Create pools, with created crush_rules in group_vars/clients.yml file.

Example

```
copy_admin_key: True
user_config: True
pool1:
    name: "pool1"
    pg_num: 128
    pgp_num: 128
    rule_name: "HDD"
    type: "replicated"
    device_class: "hdd"
pools:
    - "{{ pool1 }}"
```

3. Sample the inventory file to assign roots to OSDs:

Example

```
[mons]
mon1

[osds]
osd1 osd_crush_location="{ 'root': 'default', 'rack': 'rack1', 'host': 'osd1' }"
osd2 osd_crush_location="{ 'root': 'default', 'rack': 'rack1', 'host': 'osd2' }"
osd3 osd_crush_location="{ 'root': 'default', 'rack': 'rack2', 'host': 'osd3' }"
osd4 osd_crush_location="{ 'root': 'default', 'rack': 'rack2', 'host': 'osd4' }"
osd5 devices="['/dev/sda', '/dev/sdb']" osd_crush_location="{ 'root': 'default', 'rack': 'rack3', 'host': 'osd5' }"
osd6 devices="['/dev/sda', '/dev/sdb']" osd_crush_location="{ 'root': 'default', 'rack': 'rack3', 'host': 'osd6' }"

[mgrs]
mgr1

[clients]
client1
```

4. View the tree.

Syntax

[root@mon ~]# ceph osd tree

Example

TYPE NAME

```
root default
   rack rack1
     host osd1
       osd.0
       osd.10
     host osd2
       osd.3
       osd.7
       osd.12
   rack rack2
    host osd3
       osd.1
        osd.6
       osd.11
     host osd4
       osd.4
       osd.9
       osd.13
   rack rack3
     host osd5
       osd.2
       osd.8
     host osd6
       osd.14
       osd.15
```

5. Validate the pools.

Example

```
# for i in $(rados Ispools);do echo "pool: $i"; ceph osd pool get $i crush_rule;done pool: pool1 crush_rule: HDD
```

Additional Resources

- See the *Installing a Red Hat Ceph Storage Cluster* in the *Red Hat Ceph Storage Installation Guide* for more details.
- See Device Classes in Red Hat Ceph Storage Storage Strategies Guide for more details.

4.9. INSTALLING THE NFS-GANESHA GATEWAY

The Ceph NFS Ganesha Gateway is an NFS interface built on top of the Ceph Object Gateway to provide applications with a POSIX filesystem interface to the Ceph Object Gateway for migrating files within filesystems to Ceph Object Storage.

Prerequisites

- A running Ceph storage cluster, preferably in the **active + clean** state.
- At least one node running a Ceph Object Gateway.

- Disable any running kernel NFS service instances on any host that will run NFS-Ganesha before attempting to run NFS-Ganesha. NFS-Ganesha will not start if another NFS instance is running.
- Ensure the rpcbind service is running:

systemctl start rpcbind



NOTE

The rpcbind package that provides rpcbind is usually installed by default. If that is not the case, install the package first.

• If the nfs-service service is running, stop and disable it:

systemctl stop nfs-server.service # systemctl disable nfs-server.service

Procedure

Perform the following tasks on the Ansible administration node.

1. Create the **nfss.yml** file from the sample file:

```
[root@ansible ~]# cd /etc/ansible/group_vars [root@ansible ~]# cp nfss.yml.sample nfss.yml
```

2. Add gateway hosts to the /etc/ansible/hosts file under an [nfss] group to identify their group membership to Ansible.

```
[nfss]
NFS_HOST_NAME_1
NFS_HOST_NAME_2
NFS_HOST_NAME[3..10]
```

If the hosts have sequential naming, then you can use a range specifier, for example: [3..10].

3. Navigate to the Ansible configuration directory:

```
[root@ansible ~]# cd /usr/share/ceph-ansible
```

4. To copy the administrator key to the Ceph Object Gateway node, uncomment the **copy_admin_key** setting in the /**usr/share/ceph-ansible/group_vars/nfss.yml** file:

```
copy_admin_key: true
```

 Configure the FSAL (File System Abstraction Layer) sections of the /usr/share/cephansible/group_vars/nfss.yml file. Provide an export ID (NUMERIC_EXPORT_ID), S3 user ID (S3_USER), S3 access key (ACCESS_KEY) and secret key (SECRET_KEY):

```
# FSAL RGW Config #

ceph_nfs_rgw_export_id: NUMERIC_EXPORT_ID

#ceph_nfs_rgw_pseudo_path: "/"
```

#ceph_nfs_rgw_protocols: "3,4" #ceph_nfs_rgw_access_type: "RW" ceph_nfs_rgw_user: "*S3_USER*"

ceph_nfs_rgw_access_key: "ACCESS_KEY" ceph_nfs_rgw_secret_key: "SECRET_KEY"



WARNING

Access and secret keys are optional, and can be generated.

- 6. Run the Ansible playbook:
 - a. Bare-metal deployments:

[ansible@admin ceph-ansible]\$ ansible-playbook site.yml --limit nfss -i hosts

b. Container deployments:

[ansible@admin ceph-ansible]\$ ansible-playbook site-docker.yml --limit nfss -i hosts

Additional Resources

- Understanding the limit option
- Object Gateway Configuration and Administration Guide

4.10. UNDERSTANDING THE LIMIT OPTION

This section contains information about the Ansible --limit option.

Ansible supports the **--limit** option that enables you to use the **site** and **site-docker** Ansible playbooks for a particular role of the inventory file.

ansible-playbook site.yml|site-docker.yml --limit osds|rgws|clients|mdss|nfss|iscsigws -i hosts

Bare-metal

For example, to redeploy only OSDs on bare-metal, run the following command as the Ansible user:

 $[ansible@ansible\ ceph-ansible]\$\ ansible-playbook\ site.yml\ --limit\ osds\ -i\ hosts$

Containers

For example, to redeploy only OSDs on containers, run the following command as the Ansible user:

[ansible@ansible ceph-ansible]\$ ansible-playbook site-docker.yml --limit osds -i hosts



IMPORTANT

If you colocate Ceph components on one node, Ansible applies a playbook to **all components** on the node despite that only one component type was specified with the **limit** option. For example, if you run the **site** playbook with the **--limit osds** option on a node that is listed under OSDs and Metadata Servers (MDS) group in the inventory file, Ansible will run the tasks of both the components, OSDs and MDSs, on the node.

4.11. THE PLACEMENT GROUP AUTOSCALER

Placement group (PG) tuning use to be a manual process of plugging in numbers for **pg_num** by using the PG calculator. Starting with Red Hat Ceph Storage 4.1, PG tuning can be done automatically by enabling the **pg_autoscaler** Ceph manager module. The PG autoscaler is configured on a per-pool basis, and scales the **pg_num** by a power of two. The PG autoscaler only proposes a change to **pg_num**, if the suggested value is more than three times the actual value.

The PG autoscaler has three modes:

warn

The default mode for new and existing pools. A health warning is generated if the suggested **pg_num** value varies too much from the current **pg_num** value.

on

The pool's **pg_num** is adjusted automatically.

off

The autoscaler can be turned off for any pool, but storage administrators will need to manually set the **pg num** value for the pool.

Once the PG autoscaler in enabled for a pool, you can view the value adjustments by running the **ceph osd pool autoscale-status** command. The **autoscale-status** command displays the current state of the pools. Here are the **autoscale-status** column descriptions:

SIZE

Reports the total amount of data, in bytes, that are stored in the pool. This size includes object data and OMAP data.

TARGET SIZE

Reports the expected size of the pool as provided by the storage administrator. This value is used to calculate the pool's ideal number of PGs.

RATE

The replication factor for replicated buckets or the ratio for erasure-coded pools.

RAW CAPACITY

The raw storage capacity of a storage device that a pool is mapped to based on CRUSH.

RATIO

The ratio of total storage being consumed by the pool.

TARGET RATIO

A ratio specifying what fraction of the total storage cluster's space is consumed by the pool as provided by the storage administrator.

PG_NUM

The current number of placement groups for the pool.

NEW PG_NUM

The proposed value. This value might not be set.

AUTOSCALE

The PG autoscaler mode set for the pool.

Additional Resources

• The Placement group pool calculator.

4.11.1. Configuring the placement group autoscaler

You can configure Ceph Ansible to enable and configure the PG autoscaler for new pools in the Red Hat Ceph Storage cluster. By default, the placement group (PG) autoscaler is off.



IMPORTANT

Currently, you can only configure the placement group autoscaler on new Red Hat Ceph Storage deployments, and not existing Red Hat Ceph Storage installations.

Prerequisites

- Access to the Ansible administration node.
- Access to a Ceph Monitor node.

Procedure

- 1. On the Ansible administration node, open the **group_vars/all.yml** file for editing.
- Set the pg_autoscale_mode option to True, and set the target_size_ratio value for a new or existing pool:

Example

openstack_pools:

- {"name": backups, "target_size_ratio": 0.1, "pg_autoscale_mode": True, "application": rbd}
- {"name": volumes, "target_size_ratio": 0.5, "pg_autoscale_mode": True, "application": rbd}
 - {"name": vms, "target_size_ratio": 0.2, "pg_autoscale_mode": True, "application": rbd}
 - {"name": images, "target_size_ratio": 0.2, "pg_autoscale_mode": True, "application": rbd}



NOTE

The **target_size_ratio** value is the weight percentage relative to other pools in the storage cluster.

- 3. Save the changes to the **group_vars/all.yml** file.
- 4. Run the appropriate Ansible playbook:

Bare-metal deployments

[ansible@admin ceph-ansible]\$ ansible-playbook site.yml -i hosts

Containers deployments

- [ansible@admin ceph-ansible]\$ ansible-playbook site-docker.yml -i hosts
- 5. Once the Ansible playbook finishes, check the autoscaler status from a Ceph Monitor node:

[user@mon ~]\$ ceph osd pool autoscale-status

4.12. ADDITIONAL RESOURCES

• The Ansible Documentation

CHAPTER 5. COLOCATION OF CONTAINERIZED CEPH DAEMONS

This section describes:

- How colocation works and its advantages
- How to set dedicated resources for colocated daemons

5.1. HOW COLOCATION WORKS AND ITS ADVANTAGES

You can colocate containerized Ceph daemons on the same node. Here are the advantages of colocating some of Ceph's services:

- Significant improvement in total cost of ownership (TCO) at small scale
- Reduction from six nodes to three for the minimum configuration
- Easier upgrade
- Better resource isolation

How Colocation Works

You can colocate one daemon from the following list with an OSD daemon by adding the same node to appropriate sections in the Ansible inventory file.

- Ceph Object Gateway (radosgw)
- Ceph Metadata Server (MDS)
- RBD mirror (**rbd-mirror**)
- Ceph Monitor and the Ceph Manager daemon (ceph-mgr)
- NFS Ganesha

The following example shows how the inventory file with colocated daemons can look like:

Ansible inventory file with colocated daemons

```
[mons]

MONITOR_NODE_NAME_1

MONITOR_NODE_NAME_2

MONITOR_NODE_NAME_3

[mgrs]

MONITOR_NODE_NAME_1

MONITOR_NODE_NAME_2

MONITOR_NODE_NAME_3

[osds]

OSD_NODE_NAME_1

OSD_NODE_NAME_2

OSD_NODE_NAME_3
```


[rgws]

RGW_NODE_NAME_1

RGW_NODE_NAME_2


The Figure 5.1, "Colocated Daemons" and Figure 5.2, "Non-colocated Daemons" images shows the difference between clusters with colocated and non-colocated daemons.

Figure 5.1. Colocated Daemons



CEPH_459072_1017

Figure 5.2. Non-colocated Daemons



CEPH_459072_1017

When you colocate two containerized Ceph daemons on a same node, the **ceph-ansible** playbook reserves dedicated CPU and RAM resources to each. By default, **ceph-ansible** uses values listed in the Recommended Minimum Hardware chapter in the Red Hat Ceph Storage Hardware Guide. To learn how to change the default values, see the Setting Dedicated Resources for Colocated Daemons section.

5.2. SETTING DEDICATED RESOURCES FOR COLOCATED DAEMONS

When colocating two Ceph daemon on the same node, the **ceph-ansible** playbook reserves CPU and RAM resources for each daemon. The default values that **ceph-ansible** uses are listed in the Recommended Minimum Hardware chapter in the Red Hat Ceph Storage Hardware Selection Guide. To change the default values, set the needed parameters when deploying Ceph daemons.

Procedure

To change the default CPU limit for a daemon, set the ceph_daemon-type_docker_cpu_limit
parameter in the appropriate .yml configuration file when deploying the daemon. See the
following table for details.

Daemon	Parameter	Configuration file
OSD	ceph_osd_docker_cpu_li mit	osds.yml
MDS	ceph_mds_docker_cpu_li mit	mdss.yml
RGW	ceph_rgw_docker_cpu_li mit	rgws.yml

For example, to change the default CPU limit to 2 for the Ceph Object Gateway, edit the /usr/share/ceph-ansible/group_vars/rgws.yml file as follows:

```
ceph_rgw_docker_cpu_limit: 2
```

 To change the default RAM for OSD daemons, set the osd_memory_target in the /usr/share/ceph-ansible/group_vars/all.yml file when deploying the daemon. For example, to limit the OSD RAM to 6 GB:

```
ceph_conf_overrides:
  osd:
  osd_memory_target=6000000000
```



IMPORTANT

In an hyperconverged infrastructure (HCI) configuration, you can also use the **ceph_osd_docker_memory_limit** parameter in the **osds.yml** configuration file to change the Docker memory CGroup limit. In this case, set **ceph_osd_docker_memory_limit** to 50% higher than **osd_memory_target**, so that the CGroup limit is more constraining than it is by default for an HCI configuration. For example, if **osd_memory_target** is set to 6 GB, set **ceph_osd_docker_memory_limit** to 9 GB:

ceph_osd_docker_memory_limit: 9g

Additional Resources

• The sample configuration files in the /usr/share/ceph-ansible/group_vars/ directory

5.3. ADDITIONAL RESOURCES

• The Red Hat Ceph Storage Hardware Selection Guide

CHAPTER 6. UPGRADING A RED HAT CEPH STORAGE CLUSTER

As a storage administrator, you can upgrade a Red Hat Ceph Storage cluster to a new major version or to a new minor version or to just apply asynchronous updates to the current version. The **rolling_update.yml** Ansible playbook performs upgrades for bare-metal or containerized deployments of Red Hat Ceph Storage. Ansible upgrades the Ceph nodes in the following order:

- Monitor nodes
- MGR nodes
- OSD nodes
- MDS nodes
- Ceph Object Gateway nodes
- All other Ceph client nodes



NOTE

Starting with Red Hat Ceph Storage 3.1 new Ansible playbooks were added to optimize storage for performance when using Object Gateway and high speed NVMe based SSDs (and SATA SSDs). The playbooks do this by placing journals and bucket indexes together on SSDs, this increases performance compared to having all journals on one device. These playbooks are designed to be used when installing Ceph. Existing OSDs continue to work and need no extra steps during an upgrade. There is no way to upgrade a Ceph cluster while simultaneously reconfiguring OSDs to optimize storage in this way. To use different devices for journals or bucket indexes requires reprovisioning OSDs. For more information see *Using NVMe with LVM optimally* in *Ceph Object Gateway for Production Guide*.



IMPORTANT

The **rolling_update.yml** playbook includes the **serial** variable that adjusts the number of nodes to be updated simultaneously. Red Hat strongly recommends to use the default value (1), which ensures that Ansible will upgrade cluster nodes one by one.



IMPORTANT

When upgrading a Red Hat Ceph Storage cluster from a previous version to version 4, the Ceph Ansible configuration will default the object store type to BlueStore. If you still want to use FileStore as the OSD object store, then explicitly set the Ceph Ansible configuration to FileStore. This ensures newly deployed and replaced OSDs are using FileStore.



IMPORTANT

When using the **rolling_update.yml** playbook to upgrade to any Red Hat Ceph Storage 4.x version, and if you are using a multisite Ceph Object Gateway configuration, then you do not have to manually update the **all.yml** file to specify the multisite configuration.



WARNING

If upgrading a multisite setup from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, heed the following recommendations or else replication may break. Set **rgw_multisite**: **false** in **all.yml** before running **rolling_update.yml**. Only upgrade a Red Hat Ceph Storage 3 cluster at version 3.3z5 or higher to Red Hat Ceph Storage 4. If you cannot update to 3.3z5 or a higher, disable synchronization between sites before upgrading the clusters. To disable synchronization, set **rgw_run_sync_thread = false** and restart the RADOS Gateway daemon. Upgrade the primary cluster first. Upgrade to Red Hat Ceph Storage 4.1 or later. To see the package versions that correlate to 3.3z5 see What are the Red Hat Ceph Storage releases and corresponding Ceph package versions?

6.1. SUPPORTED RED HAT CEPH STORAGE UPGRADE SCENARIOS

Red Hat supports the following upgrade scenarios. Read the tables for *bare-metal*, *containerized*, and *bare-metal with operating system* (OS) upgrade to understand what pre-upgrade state your cluster must be in to move to certain post-upgrade states.

Use **ceph-ansible** to perform bare-metal and containerized upgrades where the bare-metal or host OS does not change major versions. To change the bare-metal OS from Red Hat Enterprise Linux 7.8 to Red Hat Enterprise Linux 8.2 as a part of updgrading Red Hat Ceph Storage (RHCS), see the chapter on Manually upgrading a Red Hat Ceph Storage cluster and operating system .

Table 6.1. Bare-metal

Pre-upgrade state		Post-upgrade state		Supported
OS version	RHCS version	OS version	RHCS version	
Red Hat Enterprise Linux 7.7	Red Hat Ceph Storage 4.0	Red Hat Enterprise Linux 7.8	Red Hat Ceph Storage 4.1	Yes
Red Hat Enterprise Linux 7.7	Red Hat Ceph Storage 3.3z4	Red Hat Enterprise Linux 7.8	Red Hat Ceph Storage 4.1	Yes
Red Hat Enterprise Linux 8.1	Red Hat Ceph Storage 4.0	Red Hat Enterprise Linux 8.2	Red Hat Ceph Storage 4.1	Yes
Red Hat Enterprise Linux 8.2	Red Hat Ceph Storage 4.0	Red Hat Enterprise Linux 8.2	Red Hat Ceph Storage 4.1	Yes

Table 6.2. Containerized

Pre-upgrade state		Post-upgrade state			Supported	
Host OS	Container	RHCS	Host OS	Container	RHCS	
version	OS version	version	version	OS version	version	
Red Hat	Red Hat	Red Hat	Red Hat	Red Hat	Red Hat	Yes
Enterprise L	Enterprise L	Ceph Stora	Enterprise L	Enterprise L	Ceph Stora	
inux 7.7	inux 7.7	ge 3.3z4	inux 7.8	inux 8.2	ge 4.1	
Red Hat	Red Hat	Red Hat	Red Hat	Red Hat	Red Hat	Yes
Enterprise L	Enterprise L	Ceph Stora	Enterprise L	Enterprise L	Ceph Stora	
inux 7.8	inux 8.1	ge 4.0	inux 7.8	inux 8.2	ge 4.1	
Red Hat	Red Hat	Red Hat	Red Hat	Red Hat	Red Hat	Yes
Enterprise L	Enterprise L	Ceph Stora	Enterprise L	Enterprise L	Ceph Stora	
inux 8.1	inux 8.1	ge 4.0	inux 8.2	inux 8.2	ge 4.1	

Table 6.3. Bare-metal with OS upgrade

Pre-upgrade state		Post-upgrade state		Supported
OS version	RHCS version	OS version	RHCS version	
Red Hat Enterprise Linux 7.8	Red Hat Ceph Storage 4.0	Red Hat Enterprise Linux 8.2	Red Hat Ceph Storage 4.1	Yes*
Red Hat Enterprise Linux 7.8	Red Hat Ceph Storage 3.3z4	Red Hat Enterprise Linux 8.2	Red Hat Ceph Storage 4.1	Yes*

^{*} Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8 is not supported with cephansible. It is supported using the procedures in Manually upgrading a Red Hat Ceph Storage cluster and operating system.

6.2. PREPARING FOR AN UPGRADE

There are a few things to complete before you can start an upgrade of a Red Hat Ceph Storage cluster. These steps apply to both bare-metal and container deployments of a Red Hat Ceph Storage cluster, unless specified for one or the other.

Prerequisites

- Root-level access to all nodes in the storage cluster.
- If upgrading from version 3, the version 3 cluster is upgraded to the latest version of Red Hat Ceph Storage 3.



IMPORTANT

You can only upgrade to the latest version of Red Hat Ceph Storage 4. For example, if version 4.1 is available, you cannot upgrade from 3 to 4.0, you must go directly to 4.1.



IMPORTANT

If using the FileStore object store, after upgrading from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, you must migrate to BlueStore.



IMPORTANT

You cannot use **ceph-ansible** to upgrade Red Hat Ceph Storage while also upgrading Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8. You must stay on Red Hat Enterprise Linux 7. To upgrade the operating system as well, see manually upgrading to a new version of Red Hat Ceph Storage and a new major release of Red Hat Enterprise Linux.

Procedure

- 1. Log in as the **root** user on all nodes in the storage cluster.
- 2. If the Ceph nodes are not connected to the Red Hat Content Delivery Network (CDN), you can use an ISO image to upgrade Red Hat Ceph Storage by updating the local repository with the latest version of Red Hat Ceph Storage.
- 3. If upgrading Red Hat Ceph Storage from version 3 to version 4, remove an existing Ceph dashboard installation.
 - a. On the Ansible administration node, change to the **cephmetrics-ansible** directory:
 - [root@admin ~]# cd /usr/share/cephmetrics-ansible
 - b. Run the purge.yml playbook to remove an existing Ceph dashboard installation:
 - [root@admin cephmetrics-ansible]# ansible-playbook -v purge.yml
- 4. If upgrading Red Hat Ceph Storage from version 3 to version 4, on the Ansible administration node, enable the Ansible repository:
 - [root@admin ~]# subscription-manager repos --enable=rhel-7-server-ansible-2.8-rpms
- 5. On the Ansible administration node, ensure the latest versions of the **ansible** and **ceph-ansible** packages are installed.

Red Hat Enterprise Linux 7

[root@admin ~]# yum update ansible ceph-ansible

Red Hat Enterprise Linux 8

[root@admin ~]# dnf update ansible ceph-ansible

6. Edit the **group_vars/osds.yml** file. Add and set the following options:

nb_retry_wait_osd_up: 50 delay_wait_osd_up: 30

7. Edit the infrastructure-playbooks/rolling_update.yml playbook and change the health_osd_check_retries and health_osd_check_delay values to 50 and 30 respectively:

health_osd_check_retries: 50 health_osd_check_delay: 30

For each OSD node, these values cause Ansible to wait for up to 25 minutes, and will check the storage cluster health every 30 seconds, waiting before continuing the upgrade process.



NOTE

Adjust the **health_osd_check_retries** option value up or down based on the used storage capacity of the storage cluster. For example, if you are using 218 TB out of 436 TB, basically using 50% of the storage capacity, then set the **health_osd_check_retries** option to **50**.

8. If the storage cluster you want to upgrade contains Ceph Block Device images that use the **exclusive-lock** feature, ensure that all Ceph Block Device users have permissions to blacklist clients:

ceph auth caps client. ID mon 'allow r, allow command "osd blacklist" osd 'EXISTING_OSD_USER_CAPS'

- 9. If the storage cluster was originally installed using Cockpit, create a symbolic link in the /usr/share/ceph-ansible directory to the inventory file where Cockpit created it, at /usr/share/ansible-runner-service/inventory/hosts:
 - a. Change to the /usr/share/ceph-ansible directory:

cd /usr/share/ceph-ansible

b. Create the symbolic link:

In -s /usr/share/ansible-runner-service/inventory/hosts hosts

- 10. If the storage cluster was originally installed using Cockpit, copy the Cockpit generated SSH keys to the Ansible user's ~/.**ssh** directory:
 - a. Copy the keys:

cp /usr/share/ansible-runner-service/env/ssh_key.pub /home/ANSIBLE_USERNAME/.ssh/id_rsa.pub # cp /usr/share/ansible-runner-service/env/ssh_key /home/ANSIBLE_USERNAME/.ssh/id_rsa

Replace ANSIBLE_USERNAME with the username for Ansible, usually admin.

Example

cp /usr/share/ansible-runner-service/env/ssh_key.pub /home/admin/.ssh/id_rsa.pub # cp /usr/share/ansible-runner-service/env/ssh_key /home/admin/.ssh/id_rsa

b. Set the appropriate owner, group, and permissions on the key files:

```
# chown ANSIBLE_USERNAME:_ANSIBLE_USERNAME_
/home/ANSIBLE_USERNAME/.ssh/id_rsa.pub
# chown ANSIBLE_USERNAME:_ANSIBLE_USERNAME_
/home/ANSIBLE_USERNAME/.ssh/id_rsa
# chmod 644 /home/ANSIBLE_USERNAME/.ssh/id_rsa.pub
# chmod 600 /home/ANSIBLE_USERNAME/.ssh/id_rsa
```

Replace ANSIBLE_USERNAME with the username for Ansible, usually admin.

Example

```
# chown admin:admin /home/admin/.ssh/id_rsa.pub
# chown admin:admin /home/admin/.ssh/id_rsa
# chmod 644 /home/admin/.ssh/id_rsa.pub
# chmod 600 /home/admin/.ssh/id_rsa
```

Additional Resources

• See Enabling the Red Hat Ceph Storage repositories for details.

6.3. UPGRADING THE STORAGE CLUSTER USING ANSIBLE

Using the Ansible deployment tool, you can upgrade a Red Hat Ceph Storage cluster by doing a rolling upgrade. These steps apply to both bare-metal and container deployment, unless otherwise noted.

Prerequisites

- Root-level access to the Ansible administration node.
- An **ansible** user account.

Procedure

- 1. Navigate to the /usr/share/ceph-ansible/ directory:
 - [root@admin ~]# cd /usr/share/ceph-ansible/
- 2. If upgrading from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, make backup copies of the **group_vars/all.yml**, **group_vars/osds.yml**, and **group_vars/clients.yml** files:
 - [root@admin ceph-ansible]# cp group_vars/all.yml group_vars/all_old.yml [root@admin ceph-ansible]# cp group_vars/osds.yml group_vars/osds_old.yml [root@admin ceph-ansible]# cp group_vars/clients.yml group_vars/clients_old.yml
- If upgrading from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, create new copies of the group_vars/all.yml.sample, group_vars/osds.yml.sample and group_vars/clients.yml.sample files, and rename them to group_vars/all.yml,

group_vars/osds.yml, and **group_vars/clients.yml** respectively. Open and edit them accordingly, basing the changes on your previously backed up copies.

[root@admin ceph-ansible]# cp group_vars/all.yml.sample group_vars/all.yml [root@admin ceph-ansible]# cp group_vars/osds.yml.sample group_vars/osds.yml [root@admin ceph-ansible]# cp group_vars/clients.yml.sample group_vars/clients.yml

4. If upgrading to a new minor version of Red Hat Ceph Storage 4, verify the value for **grafana_container_image** in **group_vars/all.yml** is the same as in **group_vars/all.yml.sample**. If it is not the same, edit it so it is.

Example

grafana_container_image: registry.redhat.io/rhceph/rhceph-4-dashboard-rhel8:4



NOTE

The image path shown is included in **ceph-ansible** version 4.0.23-1.

- 5. Copy the latest **site.yml** or **site-docker.yml** file from the sample files:
 - a. For bare-metal deployments:
 - [root@admin ceph-ansible]# cp site.yml.sample site.yml
 - b. For container deployments:
 - [root@admin ceph-ansible]# cp site-docker.yml.sample site-docker.yml
- 6. Open the **group_vars/all.yml** file and edit the following options.
 - a. Add the **fetch_directory** option:

fetch_directory: FULL_DIRECTORY_PATH

Replace

- FULL_DIRECTORY_PATH with a writable location, such as the Ansible user's home directory.
- b. If the cluster you want to upgrade contains any Ceph Object Gateway nodes, add the **radosgw_interface** option:

radosgw_interface: INTERFACE

Replace

- INTERFACE with the interface that the Ceph Object Gateway nodes listen to.
- c. The default OSD object store is BlueStore. To keep the traditional OSD object store, you must explicitly set the **osd_objectstore** option to **filestore**:

osd objectstore: filestore



NOTE

With the **osd_objectstore** option set to **filestore**, replacing an OSD will use FileStore, instead of BlueStore.



IMPORTANT

Starting with Red Hat Ceph Storage 4, FileStore is a deprecated feature. Red Hat recommends migrating the FileStore OSDs to BlueStore OSDs.

d. Starting with Red Hat Ceph Storage 4.1, you must uncomment or set dashboard_admin_password and grafana_admin_password in /usr/share/ceph-ansible/group_vars/all.yml. Set secure passwords for each. Also set custom user names for dashboard_admin_user and grafana_admin_user.



IMPORTANT

When upgrading from 4.0 to 4.1, due to a bug, you cannot change **grafana_admin_user** or **grafana_admin_password** during or after upgrade. For the time being, ensure **grafana_admin_user** and **grafana_admin_password** are uncommented and set to the original values used before upgrade. This issue is being tracked in Bug 1848753.

- e. For both bare-metal and containers deployments:
 - i. Uncomment the **upgrade_ceph_packages** option and set it to **True**:

upgrade_ceph_packages: True

ii. Set the **ceph_rhcs_version** option to **4**:

ceph_rhcs_version: 4



NOTE

Setting the **ceph_rhcs_version** option to **4** will pull in the latest version of Red Hat Ceph Storage 4.

iii. Add the ceph_docker_registry information to all.yml:

ceph_docker_registry: registry.redhat.io ceph_docker_registry_username: *USER_NAME* ceph_docker_registry_password: *PASSWORD*

- f. For **containers** deployments:
 - i. Change the **ceph docker image** option to point to the Ceph 4 container version:

ceph_docker_image: rhceph/rhceph-4-rhel8

- 7. If upgrading from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, open the Ansible inventory file for editing, /etc/ansible/hosts by default, and add the Ceph dashboard node name or IP address under the [grafana-server] section. If this section does not exist, then also add this section along with the node name or IP address.
- 8. Switch to or log in as the Ansible user, then run the **rolling_update.yml** playbook:

[ansible@admin ceph-ansible]\$ ansible-playbook infrastructure-playbooks/rolling_update.yml -i hosts

To use the playbook only for a particular group of nodes on the Ansible inventory file, you can use the **--limit** option.

- 9. As the **root** user on the RBD mirroring daemon node, upgrade the **rbd-mirror** package manually:
 - [root@rbd ~]# yum upgrade rbd-mirror
- 10. Restart the **rbd-mirror** daemon:
 - systemctl restart ceph-rbd-mirror@CLIENT_ID
- 11. Verify the health status of the storage cluster.
 - a. For **bare-metal** deployments, log into a monitor node as the **root** user and run the Ceph status command:
 - [root@mon ~]# ceph -s
 - b. For container deployments, log into a Ceph Monitor node as the root user.
 - i. List all running containers:

Red Hat Enterprise Linux 7

[root@mon ~]# docker ps

Red Hat Enterprise Linux 8

- [root@mon ~]# podman ps
- ii. Check health status:

Red Hat Enterprise Linux 7

[root@mon ~]# docker exec ceph-mon-MONITOR_NAME ceph -s

Red Hat Enterprise Linux 8

[root@mon ~]# podman exec ceph-mon-MONITOR_NAME ceph -s

Replace

• MONITOR_NAME with the name of the Ceph Monitor container found in the previous step.

Example

[root@mon ~]# podman exec ceph-mon-mon01 ceph -s

12. Once the upgrade finishes, and if you choose to migrate the FileStore OSDs to BlueStore OSDs, then run the following Ansible playbook:

Syntax

ansible-playbook infrastructure-playbooks/filestore-to-bluestore.yml --limit OSD_NODE_TO_MIGRATE

Example

[ansible@admin ceph-ansible]\$ ansible-playbook infrastructure-playbooks/filestore-to-bluestore.yml --limit osd01

Once the migration completes do the following sub steps.

a. Open for editing the **group_vars/osds.yml** file, and set the **osd_objectstore** option to **bluestore**, for example:

osd_objectstore: bluestore

b. If you are using the **lvm_volumes** variable, then change the **journal** and **journal_vg** options to **db** and **db_vg** respectively, for example:

Before

lvm_volumes:

data: /dev/sdb
journal: /dev/sdc1
 data: /dev/sdd
journal: journal1
journal_vg: journals

After

lvm_volumes:

data: /dev/sdbdb: /dev/sdc1data: /dev/sdddb: journal1db_vg: journals

- 13. If working in an OpenStack environment, update all the **cephx** users to use the RBD profile for pools. The following commands must be run as the **root** user:
 - a. Glance users:

Syntax

ceph auth caps client.glance mon 'profile rbd' osd 'profile rbd pool=*GLANCE_POOL_NAME*'

Example

[root@mon ~]# ceph auth caps client.glance mon 'profile rbd' osd 'profile rbd pool=images'

b. Cinder users:

Syntax

ceph auth caps client.cinder mon 'profile rbd' osd 'profile rbd pool=*CINDER_VOLUME_POOL_NAME*, profile rbd pool=*NOVA_POOL_NAME*, profile rbd-read-only pool=*GLANCE_POOL_NAME*'

Example

[root@mon ~]# ceph auth caps client.cinder mon 'profile rbd' osd 'profile rbd pool=volumes, profile rbd pool=vms, profile rbd-read-only pool=images'

c. OpenStack general users:

Syntax

ceph auth caps client.openstack mon 'profile rbd' osd 'profile rbd-read-only pool=*CINDER_VOLUME_POOL_NAME*, profile rbd pool=*NOVA_POOL_NAME*, profile rbd-read-only pool=*GLANCE_POOL_NAME*'

Example

[root@mon ~]# ceph auth caps client.openstack mon 'profile rbd' osd 'profile rbd-read-only pool=volumes, profile rbd pool=vms, profile rbd-read-only pool=images'



IMPORTANT

Do these CAPS updates before performing any live client migrations. This allows clients to use the new libraries running in memory, causing the old CAPS settings to drop from cache and applying the new RBD profile settings.

14. Optional: On client nodes, restart any applications that depend on the Ceph client-side libraries.



NOTE

If you are upgrading OpenStack Nova compute nodes that have running QEMU or KVM instances or use a dedicated QEMU or KVM client, stop and start the QEMU or KVM instance because restarting the instance does not work in this case.

Additional Resources

- See *Understanding the limit option* for more details.
- See How to migrate the object store from FileStore to BlueStore in the Red Hat Ceph Storage Administration Guide for more details.

6.4. UPGRADING THE STORAGE CLUSTER USING THE COMMAND-LINE INTERFACE

You can upgrade from Red Hat Ceph Storage 3.3 to Red Hat Ceph Storage 4 while the storage cluster is running. An important difference between these versions is that Red Hat Ceph Storage 4 uses the **msgr2** protocol by default, which uses port **3300**. If it is not open, the cluster will issue a **HEALTH_WARN** error.

Here are the constraints to consider when upgrading the storage cluster:

- Red Hat Ceph Storage 4 uses msgr2 protocol by default. Ensure port 3300 is open on Ceph Monitor nodes
- Once you upgrade the **ceph-monitor** daemons from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, the Red Hat Ceph Storage 3 **ceph-osd** daemons **cannot** create new OSDs until you upgrade them to Red Hat Ceph Storage 4.
- Do not create any pools while the upgrade is in progress.

Prerequisites

• Root-level access to the Ceph Monitor, OSD, and Object Gateway nodes.

Procedure

1. Ensure that the cluster has completed at least one full scrub of all PGs while running Red Hat Ceph Storage 3. Failure to do so can cause your monitor daemons to refuse to join the quorum on start, leaving them non-functional. To ensure the cluster has completed at least one full scrub of all PGs, execute the following:

ceph osd dump | grep ^flags

To proceed with an upgrade from Red Hat Ceph Storage 3 to Red Hat Ceph Storage 4, the OSD map must include the **recovery deletes** and **purged snapdirs** flags.

2. Ensure the cluster is in a healthy and clean state.

ceph health HEALTH_OK

3. For nodes running **ceph-mon** and **ceph-manager**, execute:

subscription-manager repos --enable=rhel-7-server-rhceph-4-mon-rpms

Once the Red Hat Ceph Storage 4 package is enabled, execute the following on each of the **ceph-mon** and **ceph-manager** nodes:

```
# firewall-cmd --add-port=3300/tcp
# firewall-cmd --add-port=3300/tcp --permanent
# yum update -y
# systemctl restart ceph-mon@<mon-hostname>
# systemctl restart ceph-mgr@<mgr-hostname>
```

Replace <mon-hostname> and <mgr-hostname> with the hostname of the target host.

4. Before upgrading OSDs, set the **norebalance** flag on a Ceph Monitor node to prevent OSDs from rebalancing during upgrade.

ceph osd unset norebalance

5. On each OSD node, execute:

subscription-manager repos --enable=rhel-7-server-rhceph-4-osd-rpms

Once the Red Hat Ceph Storage 4 package is enabled, update the OSD node:

yum update -y

For each OSD daemon running on the node, execute:

systemctl restart ceph-osd@<osd-num>

Replace **<osd-num>** with the osd number to restart. Ensure all OSDs on the node have restarted before proceeding to the next OSD node.

6. After upgrading all OSD nodes, unset the **noout** flag on a Ceph Monitor node.

ceph osd unset noout

7. On Ceph Object Gateway nodes, execute:

subscription-manager repos --enable=rhel-7-server-rhceph-4-tools-rpms

Once the Red Hat Ceph Storage 4 package is enabled, update the node and restart the **ceph-rgw** daemon:

```
# yum update -y
# systemctl restart ceph-rgw@<rgw-target>
```

Replace **<rgw-target>** with the rgw target to restart.

8. For the administration node, execute:

```
# subscription-manager repos --enable=rhel-7-server-rhceph-4-tools-rpms # yum update -y
```

9. Ensure the cluster is in a healthy and clean state.

```
# ceph health
HEALTH_OK
```

10. Optional: On client nodes, restart any applications that depend on the Ceph client-side libraries.



NOTE

If you are upgrading OpenStack Nova compute nodes that have running QEMU or KVM instances or use a dedicated QEMU or KVM client, stop and start the QEMU or KVM instance because restarting the instance does not work in this case.

CHAPTER 7. MANUALLY UPGRADING A RED HAT CEPH STORAGE CLUSTER AND OPERATING SYSTEM

Normally, using **ceph-ansible**, it is not possible to upgrade Red Hat Ceph Storage and Red Hat Enterprise Linux to a new major release at the same time. For example, if you are on Red Hat Enterprise Linux 7, using **ceph-ansible**, you must stay on that version. As a system administrator, you can do this manually, however.

Use this chapter to manually upgrade a Red Hat Ceph Storage cluster at version 4.0 or 3.3z4 running on Red Hat Enterprise Linux 7.8, to a Red Hat Ceph Storage cluster at version 4.1 running on Red Hat Enterprise Linux 8.2.

7.1. PREREQUISITES

- A running Red Hat Ceph Storage cluster.
- The nodes are running Red Hat Enterprise Linux 7.8.
- The nodes are using Red Hat Ceph Storage version 3.3z4 or 4.0
- Access to the installation source for Red Hat Enterprise Linux 8.2.

7.2. MANUALLY UPGRADING CEPH MONITOR NODES AND THEIR OPERATING SYSTEMS

As a system administrator, you can manually upgrade the Ceph Monitor software on a Red Hat Ceph Storage cluster node and the Red Hat Enterprise Linux operating system to a new major release at the same time.



IMPORTANT

Perform the procedure on only one Monitor node at a time. To prevent cluster access issues, ensure the current upgraded Monitor node has returned to normal operation *prior* to proceeding to the next node.

Prerequisites

- A running Red Hat Ceph Storage cluster.
- The nodes are running Red Hat Enterprise Linux 7.8.
- The nodes are using Red Hat Ceph Storage version 3.3z4 or 4.0
- Access to the installation source for Red Hat Enterprise Linux 8.2.

Procedure

1. Stop the monitor service:

systemctl stop ceph-mon@MONITOR_ID

Replace MONITOR ID with the Monitor's ID number.

- 2. If using Red Hat Ceph Storage 3, disable the Red Hat Ceph Storage 3 repositories.
 - a. Disable the tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-3-tools-rpms
 - b. Disable the mon repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-3-mon-rpms
- 3. If using Red Hat Ceph Storage 4, disable the Red Hat Ceph Storage 4 repositories.
 - a. Disable the tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-4-tools-rpms
 - b. Disable the mon repository:
 - # subscription-manager repos --disable= rhel-7-server-rhceph-4-mon-rpms
- 4. Install the **leapp** utility. See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8.
- 5. Run through the leapp preupgrade checks. See Assessing upgradability from the command line .
- 6. Set PermitRootLogin yes in /etc/ssh/sshd_config.
- 7. Restart the OpenSSH SSH daemon:
 - # systemctl restart sshd.service
- 8. Remove the iSCSI module from the Linux kernel:
 - # modprobe -r iscsi
- 9. Perform the upgrade by following Performing the upgrade from RHEL 7 to RHEL 8 .
- 10. Reboot the node.
- 11. Enable the repositories for Red Hat Ceph Storage 4 for Red Hat Enterprise Linux 8.
 - a. Enable the tools repository:
 - # subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
 - b. Enable the mon repository:
 - # subscription-manager repos --enable=rhceph-4-mon-for-rhel-8-x86_64-rpms
- 12. Install the **ceph-mon** package:
 - # dnf install ceph-mon

- 13. If the manager service is colocated with the monitor service, install the **ceph-mgr** package:
 - # dnf install ceph-mgr
- 14. Restore the **ceph-client-admin.keyring** and **ceph.conf** files from a Monitor node which has not been upgraded yet or from a node that has already had those files restored.
- 15. Install the **leveldb** package:
 - # dnf install leveldb
- 16. Start the monitor service:
 - # systemctl start ceph-mon.target
- 17. If the manager service is colocated with the monitor service, start the manager service too:
 - # systemctl start ceph-mgr.target
- 18. Verify the monitor service came back up and is in quorum.
 - # ceph -s

On the mon: line under services:, ensure the node is listed as in quorum and not as out of quorum.

Example

- mon: 3 daemons, quorum jb-ceph4-mon, jb-ceph4-mon2, jb-ceph4-mon3 (age 2h)
- 19. If the manager service is colocated with the monitor service, verify it is up too:
 - # ceph -s

Look for the manager's node name on the mgr: line under services.

Example

- mgr: jb-ceph4-mon(active, since 2h), standbys: jb-ceph4-mon3, jb-ceph4-mon2
- 20. Repeat the above steps on all Monitor nodes until they have all been upgraded.

Additional Resources

- See Manually upgrading a Red Hat Ceph Storage cluster and operating system in the Installation Guide for more information.
- See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8 for more information.

7.3. MANUALLY UPGRADING CEPH OSD NODES AND THEIR OPERATING SYSTEMS

As a system administrator, you can manually upgrade the Ceph OSD software on a Red Hat Ceph Storage cluster node and the Red Hat Enterprise Linux operating system to a new major release at the same time.



IMPORTANT

This procedure should be performed for each OSD node in the Ceph cluster, but typically only for one OSD node at a time. A maximum of one failure domains worth of OSD nodes may be performed in parallel. For example, if per-rack replication is in use, one entire rack's OSD nodes can be upgraded in parallel. To prevent data access issues, ensure the current OSD node's OSDs have returned to normal operation and all of the cluster's PGs are in the **active+clean** state **prior** to proceeding to the next OSD.



IMPORTANT

This procedure will not work with encrypted OSD partitions as the Leapp upgrade utility does not support upgrading with OSD encryption.



IMPORTANT

If the OSDs were created using **ceph-disk**, and are still managed by **ceph-disk**, you must use **ceph-volume** to take over management of them. This is covered in an optional step below.

Prerequisites

- A running Red Hat Ceph Storage cluster.
- The nodes are running Red Hat Enterprise Linux 7.8.
- The nodes are using Red Hat Ceph Storage version 3.3z4 or 4.0
- Access to the installation source for Red Hat Enterprise Linux 8.2.

Procedure

- 1. Set the OSD **noout** flag to prevent OSDs from getting marked down during the migration:
 - # ceph osd set noout
- Set the OSD nobackfill, norecover, norrebalance, noscrub and nodeep-scrub flags to avoid unnecessary load on the cluster and to avoid any data reshuffling when the node goes down for migration:
 - # ceph osd set nobackfill # ceph osd set norecover # ceph osd set norebalance # ceph osd set noscrub # ceph osd set nodeep-scrub
- 3. Gracefully shut down all the OSD processes on the node:

systemctl stop ceph-osd.target

- 4. If using Red Hat Ceph Storage 3, disable the Red Hat Ceph Storage 3 repositories.
 - a. Disable the tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-3-tools-rpms
 - b. Disable the osd repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-3-osd-rpms
- 5. If using Red Hat Ceph Storage 4, disable the Red Hat Ceph Storage 4 repositories.
 - a. Disable the tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-4-tools-rpms
 - b. Disable the osd repository:
 - # subscription-manager repos --disable= rhel-7-server-rhceph-4-osd-rpms
- 6. Install the **leapp** utility. See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8.
- 7. Run through the leapp preupgrade checks. See Assessing upgradability from the command line .
- 8. Set PermitRootLogin yes in /etc/ssh/sshd_config.
- 9. Restart the OpenSSH SSH daemon:
 - # systemctl restart sshd.service
- 10. Remove the iSCSI module from the Linux kernel:
 - # modprobe -r iscsi
- 11. Perform the upgrade by following Performing the upgrade from RHEL 7 to RHEL 8.
- 12. Reboot the node.
- 13. Enable the repositories for Red Hat Ceph Storage 4 for Red Hat Enterprise Linux 8.
 - a. Enable the tools repository:
 - # subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
 - b. Enable the osd repository:
 - # subscription-manager repos --enable=rhceph-4-osd-for-rhel-8-x86_64-rpms
- 14. Install the ceph-osd package:

dnf install ceph-osd

15. Install the **leveldb** package:

dnf install leveldb

- 16. Restore the **ceph.conf** file from a node which has not been upgraded yet or from a node that has already had those files restored.
- 17. Unset the **noout**, **nobackfill**, **norecover**, **norrebalance**, **noscrub** and **nodeep-scrub** flags:

```
# ceph osd unset noout
```

ceph osd unset nobackfill

ceph osd unset norecover

ceph osd unset norebalance

ceph osd unset noscrub

ceph osd unset nodeep-scrub

- Optional: If the OSDs were created using ceph-disk, and are still managed by ceph-disk, you
 must use ceph-volume to take over management of them.
 - a. Mount each object storage device:

/dev/DRIVE /var/lib/ceph/osd/ceph-OSD_ID

Replace DRIVE with the storage device name and partition number.

Replace OSD_ID with the OSD ID.

Example

[root@magna023 ~]# mount /dev/sdb1 /var/lib/ceph/osd/ceph-0

Verify the *ID_NUMBER* is correct.

cat /var/lib/ceph/osd/ceph-OSD_ID/whoami

Replace OSD_ID with the OSD ID.

Example

[root@magna023 ~]# cat /var/lib/ceph/osd/ceph-0/whoami 0

Repeat the above steps for any additional object store devices.

b. Scan the newly mounted devices:

ceph-volume simple scan /var/lib/ceph/osd/ceph-*OSD_ID*

Replace OSD_ID with the OSD ID.

[root@magna023 ~]# ceph-volume simple scan /var/lib/ceph/osd/ceph-0

stderr: lsblk: /var/lib/ceph/osd/ceph-0: not a block device stderr: lsblk: /var/lib/ceph/osd/ceph-0: not a block device

stderr: Unknown device, --name=, --path=, or absolute path in /dev/ or /sys expected.

Running command: /usr/sbin/cryptsetup status /dev/sdb1

--> OSD 0 got scanned and metadata persisted to file: /etc/ceph/osd/0-0c9917f7-fce8-42aa-bdec-8c2cf2d536ba.json

--> To take over management of this scanned OSD, and disable ceph-disk and udev, run:

--> ceph-volume simple activate 0 0c9917f7-fce8-42aa-bdec-8c2cf2d536ba

Repeat the above step for any additional object store devices.

c. Activate the device:

ceph-volume simple activate OSD_ID UUID

Replace OSD_ID with the OSD ID and UUID with the UUID printed in the scan output from earlier.

Example

[root@magna023 ~]# ceph-volume simple activate 0 0c9917f7-fce8-42aa-bdec-8c2cf2d536ba

Running command: /usr/bin/ln -snf /dev/sdb2 /var/lib/ceph/osd/ceph-0/journal

Running command: /usr/bin/chown -R ceph:ceph /dev/sdb2

Running command: /usr/bin/systemctl enable ceph-volume@simple-0-0c9917f7-fce8-

42aa-bdec-8c2cf2d536ba

stderr: Created symlink /etc/systemd/system/multi-user.target.wants/ceph-volume@simple-0-0c9917f7-fce8-42aa-bdec-8c2cf2d536ba.service \rightarrow

/usr/lib/systemd/system/ceph-volume@.service.

Running command: /usr/bin/ln -sf /dev/null /etc/systemd/system/ceph-disk@.service

--> All ceph-disk systemd units have been disabled to prevent OSDs getting triggered by UDEV events

Running command: /usr/bin/systemctl enable --runtime ceph-osd@0

stderr: Created symlink /run/systemd/system/ceph-osd.target.wants/ceph-

osd@0.service → /usr/lib/systemd/system/ceph-osd@.service.

Running command: /usr/bin/systemctl start ceph-osd@0

--> Successfully activated OSD 0 with FSID 0c9917f7-fce8-42aa-bdec-8c2cf2d536ba

Repeat the above step for any additional object store devices.

19. Optional: If your OSDs were created with **ceph-volume** and you did not complete the previous step, start the OSD service now:

systemctl start ceph-osd.target

20. Activate the OSDs:

Filestore

ceph-volume lvm activate --all --filestore

BlueStore

ceph-volume lvm activate --all

21. Verify the OSDs are **up** and **in**, and in the **active+clean** state.

ceph -s

On the osd: line under services:, ensure all OSDs are up and in:

Example

osd: 3 osds: 3 up (since 8s), 3 in (since 3M)

22. Repeat the above steps on all OSD nodes until they have all been upgraded.

Additional Resources

- See Manually upgrading a Red Hat Ceph Storage cluster and operating system in the Installation Guide for more information.
- See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8 for more information.

7.4. MANUALLY UPGRADING CEPH OBJECT GATEWAY NODES AND THEIR OPERATING SYSTEMS

As a system administrator, you can manually upgrade the Ceph Object Gateway (RGW) software on a Red Hat Ceph Storage cluster node and the Red Hat Enterprise Linux operating system to a new major release at the same time.



IMPORTANT

This procedure should be performed for each RGW node in the Ceph cluster, but only for one RGW node at a time. Ensure the current upgraded RGW has returned to normal operation **prior** to proceeding to the next node to prevent any client access issues.

Prerequisites

- A running Red Hat Ceph Storage cluster.
- The nodes are running Red Hat Enterprise Linux 7.8.
- The nodes are using Red Hat Ceph Storage version 3.3z4 or 4.0
- Access to the installation source for Red Hat Enterprise Linux 8.2.

Procedure

- 1. Stop the Ceph Object Gateway service:
 - # systemctl stop ceph-radosgw.target
- 2. If using Red Hat Ceph Storage 3, disable the Red Hat Ceph Storage 3 tool repository:

- # subscription-manager repos --disable=rhel-7-server-rhceph-3-tools-rpms
- 3. If using Red Hat Ceph Storage 4, disable the Red Hat Ceph Storage 4 tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-4-tools-rpms
- 4. Install the **leapp** utility. See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8.
- 5. Run through the leapp preupgrade checks. See Assessing upgradability from the command line .
- 6. Set PermitRootLogin yes in /etc/ssh/sshd_config.
- 7. Restart the OpenSSH SSH daemon:
 - # systemctl restart sshd.service
- 8. Remove the iSCSI module from the Linux kernel:
 - # modprobe -r iscsi
- 9. Perform the upgrade by following Performing the upgrade from RHEL 7 to RHEL 8.
- 10. Reboot the node.
- 11. Enable the tools repositories for Red Hat Ceph Storage 4 for Red Hat Enterprise Linux 8.
 - # subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
- 12. Install the **ceph-radosgw** package:
 - # dnf install ceph-radosgw
- 13. Optional: Install the packages for any Ceph services that are colocated on this node. Enable additional Ceph repositories if needed.
- 14. Optional: Install the leveldb package which is needed by other Ceph services.
 - # dnf install leveldb
- 15. Restore the **ceph-client-admin.keyring** and **ceph.conf** files from a node which has not been upgraded yet or from a node that has already had those files restored.
- 16. Start the RGW service:
 - # systemctl start ceph-radosgw.target
- 17. Verify the daemon is active:
 - # ceph -s

There is an rgw: line under services:.

Example

rgw: 1 daemon active (jb-ceph4-rgw.rgw0)

18. Repeat the above steps on all Ceph Object Gateway nodes until they have all been upgraded.

Additional Resources

- See Manually upgrading a Red Hat Ceph Storage cluster and operating system in the Installation Guide for more information.
- See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8 for more information.

7.5. MANUALLY UPGRADING THE CEPH DASHBOARD NODE AND ITS OPERATING SYSTEM

As a system administrator, you can manually upgrade the Ceph Dashboard software on a Red Hat Ceph Storage cluster node and the Red Hat Enterprise Linux operating system to a new major release at the same time.

Prerequisites

- A running Red Hat Ceph Storage cluster.
- The node is running Red Hat Enterprise Linux 7.8.
- The node is running Red Hat Ceph Storage version 3.3z4 or 4.0
- Access to the installation source for Red Hat Enterprise Linux 8.2.

Procedure

- 1. Uninstall the existing dashboard from the cluster.
 - a. Change to the /usr/share/cephmetrics-ansible directory:
 - # cd /usr/share/cephmetrics-ansible
 - b. Run the **purge.yml** Ansible playbook:
 - # ansible-playbook -v purge.yml
- 2. If using Red Hat Ceph Storage 3, disable the Red Hat Ceph Storage 3 tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-3-tools-rpms
- 3. If using Red Hat Ceph Storage 4, disable the Red Hat Ceph Storage 4 tools repository:
 - # subscription-manager repos --disable=rhel-7-server-rhceph-4-tools-rpms
- 4. Install the **leapp** utility. See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8.

- 5. Run through the leapp preupgrade checks. See Assessing upgradability from the command line .
- 6. Set PermitRootLogin yes in /etc/ssh/sshd config.
- 7. Restart the OpenSSH SSH daemon:
 - # systemctl restart sshd.service
- 8. Remove the iSCSI module from the Linux kernel:
 - # modprobe -r iscsi
- 9. Perform the upgrade by following Performing the upgrade from RHEL 7 to RHEL 8.
- 10. Reboot the node.
- 11. Enable the tools repository for Red Hat Ceph Storage 4 for Red Hat Enterprise Linux 8:
 - # subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
- 12. Enable the Ansible repository:
 - # subscription-manager repos --enable=ansible-2.8-for-rhel-8-x86_64-rpms
- 13. Configure **ceph-ansible** to manage the cluster. It will install dashboard. Follow the Installation Guide instructions in Installing Red Hat Ceph Storage using Ansible , including the prerequisites.
- 14. After you run **ansible-playbook site.yml** as a part of the above procedures, the URL for the dashboard will be printed. See Installing dashboard using Ansible in the Dashboard guide for more information on locating the URL and accessing the dashboard.

Additional Resources

- See Manually upgrading a Red Hat Ceph Storage cluster and operating system in the Installation Guide for more information.
- See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8 for more information.
- See Installing dashboard using Ansible in the Dashboard guide for more information.

7.6. RECOVERING FROM AN OPERATING SYSTEM UPGRADE FAILURE ON AN OSD NODE

As a system administrator, if you have a failure when using the procedure Manually upgrading Ceph OSD nodes and their operating systems, you can recover from the failure using the following procedure. In the procedure you will do a fresh install of Red Hat Enterprise Linux 8.2 on the node and still be able to recover the OSDs without any major backfilling of data besides the writes to the OSDs that were down while they were out.



IMPORTANT

DO NOT touch the media backing the OSDs or their respective **wal.db** or **block.db** databases.

Prerequisites

- A running Red Hat Ceph Storage cluster.
- An OSD node that failed to upgrade.
- Access to the installation source for Red Hat Enterprise Linux 8.2.

Procedure

- 1. Perform a standard installation of Red Hat Enterprise Linux 8.2 on the failed node and enable the Red Hat Enterprise Linux repositories.
 - Performing a standard RHEL installation
- 2. Enable the repositories for Red Hat Ceph Storage 4 for Red Hat Enterprise Linux 8.
 - a. Enable the tools repository:
 - # subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
 - b. Enable the osd repository:
 - # subscription-manager repos --enable=rhceph-4-osd-for-rhel-8-x86_64-rpms
- 3. Install the **ceph-osd** package:
 - # dnf install ceph-osd
- 4. Restore the **ceph.conf** file to /**etc/ceph** from a node which has not been upgraded yet or from a node that has already had those files restored.
- 5. Start the OSD service:
 - # systemctl start ceph-osd.target
- 6. Activate the object store devices:
 - ceph-volume lvm activate --all
- 7. Watch the recovery of the OSDs and cluster backfill writes to recovered OSDs:
 - # ceph -w

Monitor the output until all PGs are in state active+clean.

Additional Resources

- See Manually upgrading a Red Hat Ceph Storage cluster and operating system in the Installation Guide for more information.
- See Upgrading from Red Hat Enterprise Linux 7 to Red Hat Enterprise Linux 8 for more information.

7.7. ADDITIONAL RESOURCES

• If you do not need to upgrade the operating system to a new major release, see Upgrading a Red Hat Ceph Storage cluster.

CHAPTER 8. WHAT TO DO NEXT?

This is only the beginning of what Red Hat Ceph Storage can do to help you meet the challenging storage demands of the modern data center. Here are links to more information on a variety of topics:

- Benchmarking performance and accessing performance counters, see the Benchmarking Performance chapter in the Administration Guide for Red Hat Ceph Storage 4.
- Creating and managing snapshots, see the Snapshots chapter in the Block Device Guide for Red Hat Ceph Storage 4.
- Expanding the Red Hat Ceph Storage cluster, see the Managing Cluster Size chapter in the Administration Guide for Red Hat Ceph Storage 4.
- Mirroring Ceph Block Devices, see the Block Device Mirroring chapter in the Block Device Guide for Red Hat Ceph Storage 4.
- Process management, see the Process Management chapter in the Administration Guide for Red Hat Ceph Storage 4.
- Tunable parameters, see the Configuration Guide for Red Hat Ceph Storage 4.
- Using Ceph as the back end storage for OpenStack, see the Back-ends section in the Storage Guide for Red Hat OpenStack Platform.
- Monitor the health and capacity of the Red Hat Ceph Storage cluster with the Ceph Dashboard. See the link: Dashboard Guide for additional details.

APPENDIX A. TROUBLESHOOTING

A.1. ANSIBLE STOPS INSTALLATION BECAUSE IT DETECTS LESS DEVICES THAN EXPECTED

The Ansible automation application stops the installation process and returns the following error:

```
- name: fix partitions gpt header or labels of the osd disks (autodiscover disks)
    shell: "sgdisk --zap-all --clear --mbrtogpt -- '/dev/{{ item.0.item.key }}' || sgdisk --zap-all --clear --
mbrtogpt -- '/dev/{{ item.0.item.key }}'''
    with_together:
    - "{{ osd_partition_status_results.results }}"
    - "{{ ansible_devices }}"
    changed_when: false
    when:
    - ansible_devices is defined
    - item.0.item.value.removable == "0"
```

- item.0.item.value.partitions|count == 0
- item.0.rc != 0

What this means:

When the **osd_auto_discovery** parameter is set to **true** in the /**etc/ansible/group_vars/osds.yml** file, Ansible automatically detects and configures all the available devices. During this process, Ansible expects that all OSDs use the same devices. The devices get their names in the same order in which Ansible detects them. If one of the devices fails on one of the OSDs, Ansible fails to detect the failed device and stops the whole installation process.

Example situation:

- 1. Three OSD nodes (host1, host2, host3) use the /dev/sdb, /dev/sdc, and dev/sdd disks.
- 2. On **host2**, the /**dev/sdc** disk fails and is removed.
- 3. Upon the next reboot, Ansible fails to detect the removed /dev/sdc disk and expects that only two disks will be used for host2, /dev/sdb and /dev/sdc (formerly /dev/sdd).
- 4. Ansible stops the installation process and returns the above error message.

To fix the problem:

In the /etc/ansible/hosts file, specify the devices used by the OSD node with the failed disk (host2 in the Example situation above):

```
[osds]
host1
host2 devices="[ '/dev/sdb', '/dev/sdc' ]"
host3
```

See Chapter 4, Installing Red Hat Ceph Storage using Ansible for details.

APPENDIX B. USING THE COMMAND-LINE INTERFACE TO INSTALL THE CEPH SOFTWARE

As a storage administrator, you can choose to manually install various components of the Red Hat Ceph Storage software.

B.1. INSTALLING THE CEPH COMMAND LINE INTERFACE

The Ceph command-line interface (CLI) enables administrators to execute Ceph administrative commands. The CLI is provided by the **ceph-common** package and includes the following utilities:

- ceph
- ceph-authtool
- ceph-dencoder
- rados

Prerequisites

• A running Ceph storage cluster, preferably in the active + clean state.

Procedure

- 1. On the client node, enable the Red Hat Ceph Storage 4 Tools repository:
 - [root@gateway ~]# subscription-manager repos --enable=rhceph-4-mon-for-rhel-8-x86_64-rpms
- 2. On the client node, install the **ceph-common** package:
 - # yum install ceph-common
- 3. From the initial monitor node, copy the Ceph configuration file, in this case **ceph.conf**, and the administration keyring to the client node:

Syntax

scp /etc/ceph/ceph.conf <user_name>@<client_host_name>:/etc/ceph/ # scp /etc/ceph/ceph.client.admin.keyring <user_name>@<client_host_name:/etc/ceph/

Example

scp /etc/ceph/ceph.conf root@node1:/etc/ceph/ # scp /etc/ceph/ceph.client.admin.keyring root@node1:/etc/ceph/

Replace **<cli>ent host name>** with the host name of the client node.

B.2. MANUALLY INSTALLING RED HAT CEPH STORAGE



IMPORTANT

Red Hat does not support or test upgrading manually deployed clusters. Therefore, Red Hat recommends to use Ansible to deploy a new cluster with Red Hat Ceph Storage 4. See Chapter 4, Installing Red Hat Ceph Storage using Ansible for details.

You can use command-line utilities, such as Yum, to upgrade manually deployed clusters, but Red Hat does not support or test this approach.

All Ceph clusters require at least one monitor, and at least as many OSDs as copies of an object stored on the cluster. Red Hat recommends using three monitors for production environments and a minimum of three Object Storage Devices (OSD).

Bootstrapping the initial monitor is the first step in deploying a Ceph storage cluster. Ceph monitor deployment also sets important criteria for the entire cluster, such as:

- The number of replicas for pools
- The number of placement groups per OSD
- The heartheat intervals
- Any authentication requirement

Most of these values are set by default, so it is useful to know about them when setting up the cluster for production.

Installing a Ceph storage cluster by using the command line interface involves these steps:

- Bootstrapping the initial Monitor node
- Adding an Object Storage Device (OSD) node

Monitor Bootstrapping

Bootstrapping a Monitor and by extension a Ceph storage cluster, requires the following data:

Unique Identifier

The File System Identifier (**fsid**) is a unique identifier for the cluster. The **fsid** was originally used when the Ceph storage cluster was principally used for the Ceph file system. Ceph now supports native interfaces, block devices, and object storage gateway interfaces too, so **fsid** is a bit of a misnomer.

Monitor Name

Each Monitor instance within a cluster has a unique name. In common practice, the Ceph Monitor name is the node name. Red Hat recommend one Ceph Monitor per node, and no co-locating the Ceph OSD daemons with the Ceph Monitor daemon. To retrieve the short node name, use the **hostname -s** command.

Monitor Map

Bootstrapping the initial Monitor requires you to generate a Monitor map. The Monitor map requires:

- The File System Identifier (fsid)
- The cluster name, or the default cluster name of ceph is used
- At least one host name and its IP address.

Monitor Keyring

Monitors communicate with each other by using a secret key. You must generate a keyring with a Monitor secret key and provide it when bootstrapping the initial Monitor.

Administrator Keyring

To use the **ceph** command-line interface utilities, create the **client.admin** user and generate its keyring. Also, you must add the **client.admin** user to the Monitor keyring.

The foregoing requirements do not imply the creation of a Ceph configuration file. However, as a best practice, Red Hat recommends creating a Ceph configuration file and populating it with the **fsid**, the **mon initial members** and the **mon host** settings at a minimum.

You can get and set all of the Monitor settings at runtime as well. However, the Ceph configuration file might contain only those settings which overrides the default values. When you add settings to a Ceph configuration file, these settings override the default settings. Maintaining those settings in a Ceph configuration file makes it easier to maintain the cluster.

To bootstrap the initial Monitor, perform the following steps:

1. Enable the Red Hat Ceph Storage 4 Monitor repository:

 $[root@monitor ~] \# \ subscription-manager \ repos --enable = rhceph-4-mon-for-rhel-8-x86_64-rpms$

- 2. On your initial Monitor node, install the **ceph-mon** package as **root**:
 - # yum install ceph-mon
- 3. As **root**, create a Ceph configuration file in the /etc/ceph/ directory.
 - # touch /etc/ceph/ceph.conf
- 4. As **root**, generate the unique identifier for your cluster and add the unique identifier to the **[global]** section of the Ceph configuration file:

```
# echo "[global]" > /etc/ceph/ceph.conf
# echo "fsid = `uuidgen`" >> /etc/ceph/ceph.conf
```

5. View the current Ceph configuration file:

```
$ cat /etc/ceph/ceph.conf
[global]
fsid = a7f64266-0894-4f1e-a635-d0aeaca0e993
```

6. As **root**, add the initial Monitor to the Ceph configuration file:

Syntax

```
# echo "mon initial members = <monitor_host_name>[,<monitor_host_name>]" >>
/etc/ceph/ceph.conf
```

echo "mon initial members = node1" >> /etc/ceph/ceph.conf

7. As **root**, add the IP address of the initial Monitor to the Ceph configuration file:

Syntax

echo "mon host = <ip-address>[,<ip-address>]" >> /etc/ceph/ceph.conf

Example

echo "mon host = 192.168.0.120" >> /etc/ceph/ceph.conf



NOTE

To use IPv6 addresses, you set the **ms bind ipv6** option to **true**. For details, see the Bind section in the Configuration Guide for Red Hat Ceph Storage 4.

8. As **root**, create the keyring for the cluster and generate the Monitor secret key:

ceph-authtool --create-keyring /tmp/ceph.mon.keyring --gen-key -n mon. --cap mon 'allow *' creating /tmp/ceph.mon.keyring

9. As **root**, generate an administrator keyring, generate a **ceph.client.admin.keyring** user and add the user to the keyring:

Syntax

ceph-authtool --create-keyring /etc/ceph/ceph.client.admin.keyring --gen-key -n client.admin --set-uid=0 --cap mon '<capabilites>' --cap osd '<capabilites>' --cap mds '<capabilites>'

Example

ceph-authtool --create-keyring /etc/ceph/ceph.client.admin.keyring --gen-key -n client.admin --set-uid=0 --cap mon 'allow *' --cap osd 'allow *' --cap mds 'allow' creating /etc/ceph/ceph.client.admin.keyring

10. As **root**, add the **ceph.client.admin.keyring** key to the **ceph.mon.keyring**:

ceph-authtool /tmp/ceph.mon.keyring --import-keyring /etc/ceph/ceph.client.admin.keyring importing contents of /etc/ceph/ceph.client.admin.keyring into /tmp/ceph.mon.keyring

11. Generate the Monitor map. Specify using the node name, IP address and the **fsid**, of the initial Monitor and save it as /tmp/monmap:

Syntax

\$ monmaptool --create --add <monitor_host_name> <ip-address> --fsid <uuid>
/tmp/monmap

\$ monmaptool --create --add node1 192.168.0.120 --fsid a7f64266-0894-4f1e-a635-

d0aeaca0e993 /tmp/monmap

monmaptool: monmap file /tmp/monmap

monmaptool: set fsid to a7f64266-0894-4f1e-a635-d0aeaca0e993

monmaptool: writing epoch 0 to /tmp/monmap (1 monitors)

12. As **root** on the initial Monitor node, create a default data directory:

Syntax

mkdir /var/lib/ceph/mon/ceph-<monitor_host_name>

Example

mkdir /var/lib/ceph/mon/ceph-node1

13. As **root**, populate the initial Monitor daemon with the Monitor map and keyring:

Syntax

ceph-mon --mkfs -i <monitor_host_name> --monmap /tmp/monmap --keyring /tmp/ceph.mon.keyring

Example

ceph-mon --mkfs -i node1 --monmap /tmp/monmap --keyring /tmp/ceph.mon.keyring ceph-mon: set fsid to a7f64266-0894-4f1e-a635-d0aeaca0e993 ceph-mon: created monfs at /var/lib/ceph/mon/ceph-node1 for mon.node1

14. View the current Ceph configuration file:

```
# cat /etc/ceph/ceph.conf
[global]
fsid = a7f64266-0894-4f1e-a635-d0aeaca0e993
mon_initial_members = node1
mon_host = 192.168.0.120
```

For more details on the various Ceph configuration settings, see the Configuration Guide for Red Hat Ceph Storage 4. The following example of a Ceph configuration file lists some of the most common configuration settings:

```
[global]
fsid = <cluster-id>
mon initial members = <monitor_host_name>[, <monitor_host_name>]
mon host = <ip-address>[, <ip-address>]
public network = <network>[, <network>]
cluster network = <network>[, <network>]
auth cluster required = cephx
auth service required = cephx
osd journal size = <n>
```

```
osd pool default size = <n> # Write an object n times.
osd pool default min size = <n> # Allow writing n copy in a degraded state.
osd pool default pg num = <n>
osd pool default pgp num = <n>
osd crush chooseleaf type = <n>
```

15. As **root**, create the **done** file:

Syntax

touch /var/lib/ceph/mon/ceph-<monitor_host_name>/done

Example

touch /var/lib/ceph/mon/ceph-node1/done

16. As **root**, update the owner and group permissions on the newly created directory and files:

Syntax

```
# chown -R <owner>:<group> <path_to_directory>
```

Example

```
# chown -R ceph:ceph /var/lib/ceph/mon
# chown -R ceph:ceph /var/log/ceph
# chown -R ceph:ceph /var/run/ceph
# chown ceph:ceph /etc/ceph/ceph.client.admin.keyring
# chown ceph:ceph /etc/ceph/ceph.conf
# chown ceph:ceph /etc/ceph/rbdmap
```



NOTE

If the Ceph Monitor node is co-located with an OpenStack Controller node, then the Glance and Cinder keyring files must be owned by **glance** and **cinder** respectively. For example:

```
# Is -I /etc/ceph/
...
-rw-----. 1 glance glance 64 <date> ceph.client.glance.keyring
-rw-----. 1 cinder cinder 64 <date> ceph.client.cinder.keyring
...
```

17. As **root**, start and enable the **ceph-mon** process on the initial Monitor node:

Syntax

```
# systemctl enable ceph-mon.target
# systemctl enable ceph-mon@<monitor_host_name>
# systemctl start ceph-mon@<monitor_host_name>
```

Example

systemctl enable ceph-mon.target # systemctl enable ceph-mon@node1 # systemctl start ceph-mon@node1

18. As **root**, verify the monitor daemon is running:

Syntax

systemctl status ceph-mon@<monitor_host_name>

Example

systemctl status ceph-mon@node1

ceph-mon@node1.service - Ceph cluster monitor daemon
 Loaded: loaded (/usr/lib/systemd/system/ceph-mon@.service; enabled; vendor preset:
 disabled)

Active: active (running) since Wed 2018-06-27 11:31:30 PDT; 5min ago

Main PID: 1017 (ceph-mon)

CGroup: /system.slice/system-ceph\x2dmon.slice/ceph-mon@node1.service

1017 /usr/bin/ceph-mon -f --cluster ceph --id node1 --setuser ceph --setgroup ceph

Jun 27 11:31:30 node1 systemd[1]: Started Ceph cluster monitor daemon. Jun 27 11:31:30 node1 systemd[1]: Starting Ceph cluster monitor daemon...

To add more Red Hat Ceph Storage Monitors to the storage cluster, see the Adding a Monitor section in the Administration Guide for Red Hat Ceph Storage 4.

OSD Bootstrapping

Once you have your initial monitor running, you can start adding the Object Storage Devices (OSDs). Your cluster cannot reach an **active + clean** state until you have enough OSDs to handle the number of copies of an object.

The default number of copies for an object is three. You will need three OSD nodes at minimum. However, if you only want two copies of an object, therefore only adding two OSD nodes, then update the **osd pool default size** and **osd pool default min size** settings in the Ceph configuration file.

For more details, see the OSD Configuration Reference section in the Configuration Guide for Red Hat Ceph Storage 4.

After bootstrapping the initial monitor, the cluster has a default CRUSH map. However, the CRUSH map does not have any Ceph OSD daemons mapped to a Ceph node.

To add an OSD to the cluster and updating the default CRUSH map, execute the following on each OSD node:

1. Enable the Red Hat Ceph Storage 4 OSD repository:

[root@osd ~]# subscription-manager repos --enable=rhceph-4-osd-for-rhel-8-x86_64-rpms

2. As **root**, install the **ceph-osd** package on the Ceph OSD node:

yum install ceph-osd

3. Copy the Ceph configuration file and administration keyring file from the initial Monitor node to the OSD node:

Syntax

```
# scp <user_name>@<monitor_host_name>:<path_on_remote_system>
<path_to_local_file>
```

Example

```
# scp root@node1:/etc/ceph/ceph.conf /etc/ceph
# scp root@node1:/etc/ceph/ceph.client.admin.keyring /etc/ceph
```

4. Generate the Universally Unique Identifier (UUID) for the OSD:

```
$ uuidgen
b367c360-b364-4b1d-8fc6-09408a9cda7a
```

5. As **root**, create the OSD instance:

Syntax

```
# ceph osd create <uuid> [<osd_id>]
```

Example

```
# ceph osd create b367c360-b364-4b1d-8fc6-09408a9cda7a
0
```



NOTE

This command outputs the OSD number identifier needed for subsequent steps.

6. As **root**, create the default directory for the new OSD:

Syntax

mkdir /var/lib/ceph/osd/ceph-<osd_id>

Example

mkdir /var/lib/ceph/osd/ceph-0

7. As **root**, prepare the drive for use as an OSD, and mount it to the directory you just created. Create a partition for the Ceph data and journal. The journal and the data partitions can be located on the same disk. This example is using a 15 GB disk:

Syntax

```
# parted <path_to_disk> mklabel gpt
# parted <path_to_disk> mkpart primary 1 10000
```

```
# mkfs -t <fstype> <path_to_partition>
# mount -o noatime <path_to_partition> /var/lib/ceph/osd/ceph-<osd_id>
# echo "<path_to_partition> /var/lib/ceph/osd/ceph-<osd_id> xfs defaults,noatime 1 2" >>
/etc/fstab
```

Example

```
# parted /dev/sdb mklabel gpt
# parted /dev/sdb mkpart primary 1 10000
# parted /dev/sdb mkpart primary 10001 15000
# mkfs -t xfs /dev/sdb1
# mount -o noatime /dev/sdb1 /var/lib/ceph/osd/ceph-0
# echo "/dev/sdb1 /var/lib/ceph/osd/ceph-0 xfs defaults,noatime 1 2" >> /etc/fstab
```

8. As **root**, initialize the OSD data directory:

Syntax

ceph-osd -i <osd_id> --mkfs --mkkey --osd-uuid <uuid>

Example

```
# ceph-osd -i 0 --mkfs --mkkey --osd-uuid b367c360-b364-4b1d-8fc6-09408a9cda7a ... auth: error reading file: /var/lib/ceph/osd/ceph-0/keyring: can't open /var/lib/ceph/osd/ceph-0/keyring: (2) No such file or directory ... created new key in keyring /var/lib/ceph/osd/ceph-0/keyring
```

9. As **root**, register the OSD authentication key.

Syntax

ceph auth add osd.<osd_id> osd 'allow *' mon 'allow profile osd' -i /var/lib/ceph/osd/ceph-cosd_id>/keyring

Example

ceph auth add osd.0 osd 'allow *' mon 'allow profile osd' -i /var/lib/ceph/osd/ceph-0/keyring added key for osd.0

10. As **root**, add the OSD node to the CRUSH map:

Syntax

ceph osd crush add-bucket <host_name> host

Example

ceph osd crush add-bucket node2 host

11. As **root**, place the OSD node under the **default** CRUSH tree:

Syntax

ceph osd crush move <host_name> root=default

Example

ceph osd crush move node2 root=default

12. As root, add the OSD disk to the CRUSH map

Syntax

ceph osd crush add osd.<osd_id> <weight> [<bucket_type>=<bucket-name> ...]

Example

ceph osd crush add osd.0 1.0 host=node2 add item id 0 name 'osd.0' weight 1 at location {host=node2} to crush map



NOTE

You can also decompile the CRUSH map, and add the OSD to the device list. Add the OSD node as a bucket, then add the device as an item in the OSD node, assign the OSD a weight, recompile the CRUSH map and set the CRUSH map. For more details, see the Editing a CRUSH map section in the *Storage Strategies Guide* for Red Hat Ceph Storage 4 for more details.

13. As **root**, update the owner and group permissions on the newly created directory and files:

Syntax

chown -R <owner>:<group> <path_to_directory>

Example

```
# chown -R ceph:ceph /var/lib/ceph/osd
# chown -R ceph:ceph /var/log/ceph
# chown -R ceph:ceph /var/run/ceph
# chown -R ceph:ceph /etc/ceph
```

14. The OSD node is in your Ceph storage cluster configuration. However, the OSD daemon is **down** and **in**. The new OSD must be **up** before it can begin receiving data. As **root**, enable and start the OSD process:

Syntax

```
# systemctl enable ceph-osd.target
# systemctl enable ceph-osd@<osd_id>
# systemctl start ceph-osd@<osd_id>
```

```
# systemctl enable ceph-osd.target
# systemctl enable ceph-osd@0
# systemctl start ceph-osd@0
```

Once you start the OSD daemon, it is **up** and **in**.

Now you have the monitors and some OSDs up and running. You can watch the placement groups peer by executing the following command:

\$ ceph -w

To view the OSD tree, execute the following command:

\$ ceph osd tree

Example

ID	WEIG	HT TYPE NAI	ME	UP/DOWI	N REWEIGHT	PRIMARY-AFFINITY
-1	2	root default				
-2	2	host node2				
0	1	osd.0	up	1	1	
-3	1	host node3				
1	1	osd.1	up	1	1	

To expand the storage capacity by adding new OSDs to the storage cluster, see the Adding an OSD section in the *Administration Guide* for Red Hat Ceph Storage 4.

B.3. MANUALLY INSTALLING CEPH MANAGER

Usually, the Ansible automation utility installs the Ceph Manager daemon (**ceph-mgr**) when you deploy the Red Hat Ceph Storage cluster. However, if you do not use Ansible to manage Red Hat Ceph Storage, you can install Ceph Manager manually. Red Hat recommends to colocate the Ceph Manager and Ceph Monitor daemons on a same node.

Prerequisites

- A working Red Hat Ceph Storage cluster
- root or sudo access
- The **rhceph-4-mon-for-rhel-8-x86_64-rpms** repository enabled
- Open ports **6800-7300** on the public network if firewall is used

Procedure

Use the following commands on the node where **ceph-mgr** will be deployed and as the **root** user or with the **sudo** utility.

1. Install the **ceph-mgr** package:

[root@node1 ~]# yum install ceph-mgr

2. Create the /var/lib/ceph/mgr/ceph-hostname/ directory:

mkdir /var/lib/ceph/mgr/ceph-hostname

Replace *hostname* with the host name of the node where the **ceph-mgr** daemon will be deployed, for example:

[root@node1 ~]# mkdir /var/lib/ceph/mgr/ceph-node1

3. In the newly created directory, create an authentication key for the **ceph-mgr** daemon:

[root@node1 ~]# ceph auth get-or-create mgr.`hostname -s` mon 'allow profile mgr' osd 'allow *' mds 'allow *' -o /var/lib/ceph/mgr/ceph-node1/keyring

4. Change the owner and group of the /var/lib/ceph/mgr/ directory to ceph:ceph:

[root@node1 ~]# chown -R ceph:ceph /var/lib/ceph/mgr

5. Enable the **ceph-mgr** target:

[root@node1 ~]# systemctl enable ceph-mgr.target

6. Enable and start the **ceph-mgr** instance:

systemctl enable ceph-mgr@hostname systemctl start ceph-mgr@hostname

Replace *hostname* with the host name of the node where the **ceph-mgr** will be deployed, for example:

```
[root@node1 ~]# systemctl enable ceph-mgr@node1 [root@node1 ~]# systemctl start ceph-mgr@node1
```

7. Verify that the **ceph-mgr** daemon started successfully:

ceph -s

The output will include a line similar to the following one under the **services:** section:

mgr: node1(active)

8. Install more **ceph-mgr** daemons to serve as standby daemons that become active if the current active daemon fails.

Additional resources

Requirements for Installing Red Hat Ceph Storage

B.4. MANUALLY INSTALLING CEPH BLOCK DEVICE

The following procedure shows how to install and mount a thin-provisioned, resizable Ceph Block Device.



IMPORTANT

Ceph Block Devices must be deployed on separate nodes from the Ceph Monitor and OSD nodes. Running kernel clients and kernel server daemons on the same node can lead to kernel deadlocks.

Prerequisites

- Ensure to perform the tasks listed in the Section B.1, "Installing the Ceph Command Line Interface" section.
- If you use Ceph Block Devices as a back end for virtual machines (VMs) that use QEMU, increase the default file descriptor. See the Ceph VM hangs when transferring large amounts of data to RBD disk Knowledgebase article for details.

Procedure

1. Create a Ceph Block Device user named **client.rbd** with full permissions to files on OSD nodes (**osd 'allow rwx'**) and output the result to a keyring file:

ceph auth get-or-create client.rbd mon 'profile rbd' osd 'profile rbd pool=<pool_name>' \
-o /etc/ceph/rbd.keyring

Replace <pool_name> with the name of the pool that you want to allow client.rbd to have access to, for example rbd:

ceph auth get-or-create \
client.rbd mon 'allow r' osd 'allow rwx pool=rbd' \
-o /etc/ceph/rbd.keyring

See the *User Management* section in the Red Hat Ceph Storage 4 *Administration Guide* for more information about creating users.

2. Create a block device image:

```
rbd create <image_name> --size <image_size> --pool <pool_name> \
--name client.rbd --keyring /etc/ceph/rbd.keyring
```

Specify <image_name>, <image_size>, and <pool_name>, for example:

```
$ rbd create image1 --size 4G --pool rbd \
--name client.rbd --keyring /etc/ceph/rbd.keyring
```



WARNING

The default Ceph configuration includes the following Ceph Block Device features:

- layering
- exclusive-lock
- object-map
- deep-flatten
- fast-diff

If you use the kernel RBD (**krbd**) client, you may not be able to map the block device image.

To work around this problem, disable the unsupported features. Use one of the following options to do so:

- Disable the unsupported features dynamically:
 - rbd feature disable <image_name> <feature_name>

For example:

- # rbd feature disable image1 object-map deep-flatten fast-diff
- Use the --image-feature layering option with the rbd create command to enable only layering on newly created block device images.
- Disable the features be default in the Ceph configuration file:
 - rbd_default_features = 1

This is a known issue, for details see the *Known Issues* chapter in the *Release Notes* for Red Hat Ceph Storage 4.

All these features work for users that use the user-space RBD client to access the block device images.

3. Map the newly created image to the block device:

rbd map <image_name> --pool <pool_name>\
--name client.rbd --keyring /etc/ceph/rbd.keyring

For example:

rbd map image1 --pool rbd --name client.rbd \
--keyring /etc/ceph/rbd.keyring

4. Use the block device by creating a file system:

mkfs.ext4 /dev/rbd/<pool_name>/<image_name>

Specify the pool name and the image name, for example:

mkfs.ext4 /dev/rbd/rbd/image1

This action can take a few moments.

5. Mount the newly created file system:

mkdir <mount_directory>
mount /dev/rbd/<pool_name>/<image_name> <mount_directory>

For example:

mkdir /mnt/ceph-block-device # mount /dev/rbd/rbd/image1 /mnt/ceph-block-device

Additional Resources

The Block Device Guide for Red Hat Ceph Storage 4.

B.5. MANUALLY INSTALLING CEPH OBJECT GATEWAY

The Ceph object gateway, also know as the RADOS gateway, is an object storage interface built on top of the **librados** API to provide applications with a RESTful gateway to Ceph storage clusters.

Prerequisites

- A running Ceph storage cluster, preferably in the active + clean state.
- Perform the tasks listed in Chapter 2, Requirements for Installing Red Hat Ceph Storage.

Procedure

1. Enable the Red Hat Ceph Storage 4 Tools repository:

[root@gateway ~]# subscription-manager repos --enable=rhceph-4-tools-for-rhel-8-x86_64-debug-rpms

- 2. On the Object Gateway node, install the **ceph-radosgw** package:
 - # yum install ceph-radosgw
- 3. On the initial Monitor node, do the following steps.
 - a. Update the Ceph configuration file as follows:

```
[client.rgw.<obj_gw_hostname>]
host = <obj_gw_hostname>
rgw frontends = "civetweb port=80"
rgw dns name = <obj_gw_hostname>.example.com
```

Where **<obj_gw_hostname>** is a short host name of the gateway node. To view the short host name, use the **hostname -s** command.

b. Copy the updated configuration file to the new Object Gateway node and all other nodes in the Ceph storage cluster:

Syntax

scp /etc/ceph/ceph.conf <user_name>@<target_host_name>:/etc/ceph

Example

scp /etc/ceph/ceph.conf root@node1:/etc/ceph/

c. Copy the **ceph.client.admin.keyring** file to the new Object Gateway node:

Syntax

scp /etc/ceph/ceph.client.admin.keyring <user_name>@<target_host_name>:/etc/ceph/

Example

scp /etc/ceph/ceph.client.admin.keyring root@node1:/etc/ceph/

4. On the Object Gateway node, create the data directory:

mkdir -p /var/lib/ceph/radosgw/ceph-rgw.`hostname -s`

5. On the Object Gateway node, add a user and keyring to bootstrap the object gateway:

Syntax

ceph auth get-or-create client.rgw.`hostname -s` osd 'allow rwx' mon 'allow rw' -o /var/lib/ceph/radosgw/ceph-rgw.`hostname -s`/keyring

Example

ceph auth get-or-create client.rgw.`hostname -s` osd 'allow rwx' mon 'allow rw' -o /var/lib/ceph/radosgw/ceph-rgw.`hostname -s`/keyring



IMPORTANT

When you provide capabilities to the gateway key you must provide the read capability. However, providing the Monitor write capability is optional; if you provide it, the Ceph Object Gateway will be able to create pools automatically.

In such a case, ensure to specify a reasonable number of placement groups in a pool. Otherwise, the gateway uses the default number, which is most likely **not** suitable for your needs. See Ceph Placement Groups (PGs) per Pool Calculator for details.

6. On the Object Gateway node, create the **done** file:

touch /var/lib/ceph/radosgw/ceph-rgw.`hostname -s`/done

7. On the Object Gateway node, change the owner and group permissions:

```
# chown -R ceph:ceph /var/lib/ceph/radosgw
# chown -R ceph:ceph /var/log/ceph
# chown -R ceph:ceph /var/run/ceph
# chown -R ceph:ceph /etc/ceph
```

8. On the Object Gateway node, open TCP port 8080:

```
# firewall-cmd --zone=public --add-port=8080/tcp
# firewall-cmd --zone=public --add-port=8080/tcp --permanent
```

9. On the Object Gateway node, start and enable the **ceph-radosgw** process:

Syntax

```
# systemctl enable ceph-radosgw.target
# systemctl enable ceph-radosgw@rgw.<rgw_hostname>
# systemctl start ceph-radosgw@rgw.<rgw_hostname>
```

Example

```
# systemctl enable ceph-radosgw.target
# systemctl enable ceph-radosgw@rgw.node1
# systemctl start ceph-radosgw@rgw.node1
```

Once installed, the Ceph Object Gateway automatically creates pools if the write capability is set on the Monitor. See the Pools chapter in the Storage Strategies Guide for details on creating pools manually.

Additional Resources

• The Red Hat Ceph Storage 4 Object Gateway Configuration and Administration Guide

APPENDIX C. OVERRIDING CEPH DEFAULT SETTINGS

Unless otherwise specified in the Ansible configuration files, Ceph uses its default settings.

Because Ansible manages the Ceph configuration file, edit the /etc/ansible/group_vars/all.yml file to change the Ceph configuration. Use the ceph_conf_overrides setting to override the default Ceph configuration.

Ansible supports the same sections as the Ceph configuration file; **[global]**, **[mon]**, **[osd]**, **[mds]**, **[rgw]**, and so on. You can also override particular instances, such as a particular Ceph Object Gateway instance. For example:

ceph_conf_overrides:
 client.rgw.rgw1:

log_file: /var/log/ceph/ceph-rgw-rgw1.log



NOTE

Ansible does not include braces when referring to a particular section of the Ceph configuration file. Sections and settings names are terminated with a colon.



IMPORTANT

Do not set the cluster network with the **cluster_network** parameter in the **CONFIG OVERRIDE** section because this can cause two conflicting cluster networks being set in the Ceph configuration file.

To set the cluster network, use the **cluster_network** parameter in the **CEPH CONFIGURATION** section. For details, see *Installing a Red Hat Ceph Storage cluster* in the *Red Hat Ceph Storage Installation Guide*.

APPENDIX D. IMPORTING AN EXISTING CEPH CLUSTER TO ANSIBLE

You can configure Ansible to use a cluster deployed without Ansible. For example, if you upgraded Red Hat Ceph Storage 1.3 clusters to version 2 manually, configure them to use Ansible by following this procedure:

- 1. After manually upgrading from version 1.3 to version 2, install and configure Ansible on the administration node.
- 2. Ensure that the Ansible administration node has passwordless **ssh** access to all Ceph nodes in the cluster. See Section 2.11, "Enabling password-less SSH for Ansible" for more details.
- 3. As **root**, create a symbolic link to the Ansible **group_vars** directory in the /**etc/ansible**/ directory:
 - # In -s /usr/share/ceph-ansible/group_vars /etc/ansible/group_vars
- 4. As **root**, create an **all.yml** file from the **all.yml.sample** file and open it for editing:

```
# cd /etc/ansible/group_vars
# cp all.yml.sample all.yml
# vim all.yml
```

- 5. Set the **generate_fsid** setting to **false** in **group_vars/all.yml**.
- 6. Get the current cluster **fsid** by executing **ceph fsid**.
- 7. Set the retrieved **fsid** in **group vars/all.yml**.
- 8. Modify the Ansible inventory in /etc/ansible/hosts to include Ceph hosts. Add monitors under a **[mons]** section, OSDs under an **[osds]** section and gateways under an **[rgws]** section to identify their roles to Ansible.
- 9. Make sure ceph_conf_overrides is updated with the original ceph.conf options used for [global], [osd], [mon], and [client] sections in the all.yml file.
 Options like osd journal, public_network and cluster_network should not be added in ceph_conf_overrides because they are already part of all.yml. Only the options that are not part of all.yml and are in the original ceph.conf should be added to ceph_conf_overrides.
- 10. From the /usr/share/ceph-ansible/ directory run the playbook.

cd /usr/share/ceph-ansible/ # ansible-playbook infrastructure-playbooks/take-over-existing-cluster.yml -u <username> -i hosts

APPENDIX E. PURGING STORAGE CLUSTERS DEPLOYED BY ANSIBLE

If you no longer want to use a Ceph storage cluster, then use the **purge-docker-cluster.yml** playbook to remove the cluster. Purging a storage cluster is also useful when the installation process failed and you want to start over.



WARNING

After purging a Ceph storage cluster, all data on the OSDs is permanently lost.

Prerequisites

- Root-level access to the Ansible administration node.
- Access to the **ansible** user account.
- For bare-metal deployments:
 - If the osd_auto_discovery option in the /usr/share/ceph-ansible/group-vars/osds.yml file is set to true, then Ansible will fail to purge the storage cluster. Therefore, comment out osd_auto_discovery and declare the OSD devices in the osds.yml file.
- Ensure that the /var/log/ansible/ansible.log file is writable by the ansible user account.

Procedure

- 1. Navigate to the /usr/share/ceph-ansible/ directory:
 - [root@admin ~]# cd /usr/share/ceph-ansible
- 2. As the **ansible** user, run the purge playbook.
 - a. For **bare-metal** deployments, use the **purge-cluster.yml** playbook to purge the Ceph storage cluster:
 - [ansible@admin ceph-ansible]\$ ansible-playbook infrastructure-playbooks/purge-cluster.yml
 - b. For container deployments:
 - i. Use the **purge-docker-cluster.yml** playbook to purge the Ceph storage cluster:
 - [ansible@admin ceph-ansible]\$ ansible-playbook infrastructure-playbooks/purge-docker-cluster.yml



NOTE

This playbook removes all packages, containers, configuration files, and all the data created by the Ceph Ansible playbook.

ii. To specify a different inventory file other than the default (/etc/ansible/hosts), use -i parameter:

Syntax

 $[ansible@admin\ ceph-ansible]\$\ ansible-playbook\ infrastructure-playbooks/purge-docker-cluster.yml\ -i\ INVENTORY_FILE$

Replace

INVENTORY_FILE with the path to the inventory file.

Example

[ansible@admin ceph-ansible] ansible-playbook infrastructure-playbooks/purge-docker-cluster.yml -i \sim /ansible/hosts

iii. To skip the removal of the Ceph container image, use the **--skip-tags="remove_img"** option:

[ansible@admin ceph-ansible]\$ ansible-playbook --skip-tags="remove_img" infrastructure-playbooks/purge-docker-cluster.yml

iv. To skip the removal of the packages that were installed during the installation, use the -skip-tags="with_pkg" option:

[ansible@admin ceph-ansible]\$ ansible-playbook --skip-tags="with_pkg" infrastructure-playbooks/purge-docker-cluster.yml

Additional Resources

• See the OSD Ansible settings for more details.

APPENDIX F. GENERAL ANSIBLE SETTINGS

These are the most common configurable Ansible parameters. There are two sets of parameters depending on the deployment method, either bare-metal or containers.



NOTE

This is not an exhaustive list of all the available Ansible parameters.

Bare-metal and Containers Settings

monitor_interface

The interface that the Ceph Monitor nodes listen on.

Value

User-defined

Required

Yes

Notes

Assigning a value to at least one of the **monitor_*** parameters is required.

monitor address

The address that the Ceph Monitor nodes listen too.

Value

User-defined

Required

Yes

Notes

Assigning a value to at least one of the **monitor_*** parameters is required.

monitor_address_block

The subnet of the Ceph public network.

Value

User-defined

Required

Yes

Notes

Use when the IP addresses of the nodes are unknown, but the subnet is known. Assigning a value to at least one of the **monitor_*** parameters is required.

ip_version

Value

ipv6

Required

Yes, if using IPv6 addressing.

public_network

The IP address and netmask of the Ceph public network, or the corresponding IPv6 address, if using IPv6.

Value

User-defined

Required

Yes

Notes

For more information, see Verifying the Network Configuration for Red Hat Ceph Storage .

cluster_network

The IP address and netmask of the Ceph cluster network, or the corresponding IPv6 address, if using IPv6.

Value

User-defined

Required

No

Notes

For more information, see Verifying the Network Configuration for Red Hat Ceph Storage .

configure_firewall

Ansible will try to configure the appropriate firewall rules.

Value

true or false

Required

No

Bare-metal-specific Settings

ceph_origin

Value

repository or distro or local

Required

Yes

Notes

The **repository** value means Ceph will be installed through a new repository. The **distro** value means that no separate repository file will be added, and you will get whatever version of Ceph that is included with the Linux distribution. The **local** value means the Ceph binaries will be copied from the local machine.

ceph_repository_type

Value

cdn or iso

Required

Yes

```
ceph_rhcs_version
  Value
      4
   Required
      Yes
ceph_rhcs_iso_path
   The full path to the ISO image.
  Value
      User-defined
   Required
      Yes, if ceph_repository_type is set to iso.
Container-specific Settings
ceph_docker_image
  Value
      rhceph/rhceph-4-rhel8, or cephimageinlocalreg, if using a local Docker registry.
   Required
      Yes
containerized_deployment
   Value
      true
   Required
      Yes
ceph_docker_registry
  Value
      registry.redhat.io, or LOCAL_FQDN_NODE_NAME, if using a local Docker registry.
   Required
      Yes
```

APPENDIX G. OSD ANSIBLE SETTINGS

These are the most common configurable OSD Ansible parameters.

devices

List of devices where Ceph's data is stored.

Value

User-defined

Required

Yes, if specifying a list of devices.

Notes

Cannot be used when **osd_auto_discovery** setting is used. When using the **devices** option, **ceph-volume lvm batch** mode creates the optimized OSD configuration.

dmcrypt

To encrypt the OSDs.

Value

true

Required

No

Notes

The default value is false.

lvm volumes

A list of FileStore or BlueStore dictionaries.

Value

User-defined

Required

Yes, if storage devices are not defined using the **devices** parameter.

Notes

Each dictionary must contain a **data**, **journal** and **data_vg** keys. Any logical volume or volume group must be the name and not the full path. The **data**, and **journal** keys can be a logical volume (LV) or partition, but do not use one journal for multiple **data** LVs. The **data_vg** key must be the volume group containing the **data** LV. Optionally, the **journal_vg** key can be used to specify the volume group containing the journal LV, if applicable.

osds_per_device

The number of OSDs to create per device.

Value

User-defined

Required

No

Notes

The default value is 1.

osd_objectstore

The Ceph object store type for the OSDs.

Value

bluestore or filestore

Required

No

Notes

The default value is **bluestore**. Required for upgrades.