High dimensional PCA - Demo

PCA vs Sparse PCA Examples

STAT 32950-24620

Spring 2023 (5/9-11)

1/32

Example 1 - Data, Dimensions, parameters

Discussions:

- The number of observations
- The dimension = number of variables
- The "true" dimension

Simulation parameters:

$$p = 10$$

$$\sigma_1 = 290, \ \sigma_2 = 300,$$

$$c_1 = -0.3, c_2 = 0.95.$$

$$X = (X_1, \cdots, X_p) \in \mathbb{R}^p$$

PCA and sparse PCA Example 1

library(elasticnet)

Example 1 (n = p)

 $V_1 \sim N(0, \sigma_1^2), \ V_2 \sim N(0, \sigma_2^2), \ V_1, V_2$ are independent.

$$V_3 = c_1 V_1 + c_2 V_2 + \varepsilon_0.$$

 $X_i = V_1 + \varepsilon_i$, for i = 1, 2, 3, 4:

 $X_i = V_2 + \varepsilon_i$, for i = 5, 6, 7, 8;

 $X_i = V_3 + \varepsilon_i$, for i = 9, 10,

 $\varepsilon_i \sim N(0,1)$ are independent.

Data: i.i.d. samples from $X=(X_1,\cdots,X_p)\in\mathbb{R}^p$

2/32

Create data p = 10, n=10

```
# Simulated data p = 10, n=10
set.seed(246)
n=10; p1=4; p2=4; p3=2
V1=rnorm(n,mean=0,sd=(290)); V2=rnorm(n,mean=0,sd=(300))
V3 = -0.3*V1 + 0.95*V2 + rnorm(n)
Xa = matrix(0,n, p1)
for (i in 1:p1){
    Xa[,i] = V1 + rnorm(n) }
Xb = matrix(0,n, p2)
for (i in 1:p2){
    Xb[,i] = V2 + rnorm(n) }
Xc = matrix(0,n, p3)
for (i in 1:p3){
    Xc[,i] = V3 + rnorm(n) }
X = cbind(Xa,Xb,Xc)
```

PCA on raw data

```
# Variance(X_i)
round(diag(cov(X))/1000)
   [1] 60 60 60 60 157 157 158 157 136 136
# PCA use original data (p=10, n=10)
summary(princomp(X))
## Importance of components:
                            Comp.1
                                     Comp.2
                                               Comp.3
                          900.6754 464.5826 1.516e+00 1.27(
## Standard deviation
## Proportion of Variance
                            0.7898
                                     0.2102 2.239e-06 1.571
## Cumulative Proportion
                            0.7898
                                     1.0000 1.000e+00 1.000
##
                             Comp.6
                                       Comp.7
                                                 Comp.8
## Standard deviation
                          5.719e-01 4.605e-01 3.115e-01 1.2
## Proportion of Variance 3.185e-07 2.065e-07 9.445e-08 1.4
## Cumulative Proportion 1.000e+00 1.000e+00 1.000e+00 1.0
```

PCA on raw data, 2 PC's

The first two principal components:

princomp(X)\$loadings[,1:2] # Obtain first 2 PCs by PCA

```
## Comp.1 Comp.2

## [1,] 0.05138 0.489877

## [2,] 0.05167 0.489281

## [3,] 0.05179 0.489435

## [4,] 0.05094 0.489929

## [5,] 0.41721 0.004499

## [6,] 0.41779 0.005370

## [7,] 0.41848 0.005022

## [8,] 0.41787 0.005246

## [9,] 0.38135 -0.143305

## [10,] 0.38163 -0.142863
```

Each is a linear combination of all p variables.

6/32

PCA on scaled variance=1 data

PCA using var=1 data, comparable PC variance
summary(princomp(X,cor=T)) # PCA using scaled data

```
## Importance of components:
                          Comp.1 Comp.2
##
                                           Comp.3
                                                      Comp.4
## Standard deviation
                          2.4841 1.9569 4.840e-03 3.977e-03
## Proportion of Variance 0.6171 0.3829 2.343e-06 1.582e-06
## Cumulative Proportion 0.6171 1.0000 1.000e+00 1.000e+00
##
                             Comp.7
                                       Comp.8
                                                  Comp.9 Con
## Standard deviation
                          1.394e-03 1.098e-03 4.048e-04
## Proportion of Variance 1.944e-07 1.205e-07 1.639e-08
## Cumulative Proportion 1.000e+00 1.000e+00 1.000e+00
```

PCA on variance-1 data, 2 PC's

Obtain the first 2 PCs by PCA using scaled data
princomp(X,cor=T)\$loadings[,1:2]

```
## Comp.1 Comp.2
## [1,] 0.1533 0.47252
## [2,] 0.1538 0.47226
## [3,] 0.1539 0.47219
## [4,] 0.1526 0.47285
## [5,] 0.3957 -0.09372
## [6,] 0.3958 -0.09319
## [7,] 0.3958 -0.09326
## [9,] 0.3736 -0.19024
## [10,] 0.3737 -0.18990
```

7 / 32

Sparse PCA objectives

In PCA, all variables contribute to the PC's (coefficient $\neq 0$.)

Objective of Sparse PCA

- Obtain sparse PCs with few non-zero coefficients.
- The obtained sparse PCs should be good approximations of the directions of original PCs.
- Sparse PCs should capture a decent amount of data variation.

9/32

Example 1 sparse PCA (4,4)

```
# 2 PCs by spca, 4 nonzero para(meter) each (Note: var %)
spca(X, K=2, type="predictor",sparse="varnum",para=c(4,4))
##
## spca(x = X, K = 2, para = c(4, 4), type = "predictor", s
## 2 sparse PCs
## Pct. of exp. var. : 17.1 10.5
## Num. of non-zero loadings: 4 4
## Sparse loadings
##
           PC1
                  PC2
    [1,] 0.000 0.725
    [2,] 0.000 0.000
    [3,] 0.000 0.000
    [4.] 0.000 0.667
    [5,] 0.000 0.000
    [6,] 0.000 0.000
                                                     11/32
```

Sparse PCA steps

To run the sparse PCA algorithm (e.g. spca in R):

- You decide more or less variables should contribute to the PCs.
- Each sparse PC contains predetermined number of variables allowed to have non-zero coefficients.
- May use data matrix for Sparse PCA (with command type="predictor")
- May use covariance or correlation matrix for Sparse PCA (with command type="gram")

10 / 32

Example 1 sparse PCA (4,4) - Loadings

```
## PC1 PC2

## [1,] 0.00000 0.7254

## [2,] 0.00000 0.0000

## [3,] 0.00000 0.0000

## [4,] 0.00000 0.6665

## [5,] 0.00000 0.0000

## [6,] 0.00000 0.0000

## [7,] -0.99634 0.0000

## [8,] -0.08095 0.0000

## [9,] -0.01254 -0.0142

## [10,] -0.02454 -0.1713
```

Example 1 sparse PCA (4,4,2)

```
spca(X, K = 3, type = "predictor", sparse = "varnum",
    para = c(4,4,2))$loadings
            PC1
                     PC2
                             PC3
   [1,] 0.0000 0.77821 0.00000
  [2.] 0.0000 0.00000 0.00000
## [3,] 0.0000 0.08775 0.00000
## [4,] 0.0000 0.61448 0.00000
## [5,] 0.0000 0.00000 0.00000
## [6,] 0.0000 0.00000 0.00000
## [7,] -0.9709 0.00000 0.00000
## [8,] -0.1606 0.00000 0.09538
## [9,] -0.1058 0.00000 0.00000
## [10,] -0.1427 -0.09540 -0.99544
Caveat: Reduction of variance explained.
```

13 / 32

15 / 32

Sparse PCA Example 2

Example 2 (n < p)

 $V_1 \sim N(0, \sigma_1^2), \ V_2 \sim N(0, \sigma_2^2), \ V_1, V_2$ are independent. $V_3 = c_1 V_1 + c_2 V_2 + \varepsilon_0.$ $X_i = V_1 + \varepsilon_i, \ i = 1, 2, 3, 4;$ $X_i = V_2 + \varepsilon_i, \ i = 5, 6, 7, 8;$ $X_i = V_3 + \varepsilon_i, \ i = 9, 10, \cdots, 30,$ $\varepsilon_i \sim N(0, 1)$ are independent. Simulation parameters: n = 10, p = 30. Keep $\sigma_1 = 290, \ \sigma_2 = 300, \ c_1 = -0.3, c_2 = 0.95.$

14/32

Generate data for Example 2

```
# Previous example p=10, n=10 extended to p=30, n=10
p4=20
Xd = matrix(0,n, p4)
for (i in 1:p4)
{
    Xd[,i] = V3 + rnorm(n)
}
X2 = cbind(X,Xd)

dim(X)

## [1] 10 10
dim(X2)
## [1] 10 30
```

If we try PCA routine for n

In the case of n < p, classical PCA does not apply.

#princomp(X2)

 $X = (X_1, \cdots, X_p) \in \mathbb{R}^p$

R output

Error in princomp

.

'princomp' can only be used with more units than variables

.

Example 2 - Sparse PCA (30,30)

Sparse PCA works in high dimensional case n < p.

17 / 32

SPCA(10,4) Example 2: Check variation explained

```
round(t(out$loadings[13:21,1]),2)

## [,1] [,2] [,3] [,4] [,5] [,6] [,7] [,8] [,9]

## [1,] 0 0 0 0 0 0 0.05 0.4 0.27

round(t(out$loadings[22:30,1]),2)

## [,1] [,2] [,3] [,4] [,5] [,6] [,7] [,8] [,9]

## [1,] 0 0.14 0 0 0.07 0.62 0.33 0 0

out$pev

## [1] 0.24585 0.05347

Sparsity is obtained.
However variation explained can be reduced substantially.
```

Example 2 - Sparse PCA (10,4)

```
out=spca(X2, K=2, type="predictor", sparse="varnum",
        para = c(10, 10)
out$loadings[c(1:12),]
##
            PC1
                     PC2
   [1,] 0.00000 0.24192
   [2,] 0.00000 0.72858
## [3,] 0.00000 0.51198
   [4.] 0.00000 0.31754
## [5,] 0.00000 0.01885
## [6,] 0.00000 0.05074
## [7,] 0.46042 0.00000
## [8,] 0.00000 0.11044
## [9,] 0.00000 -0.02739
## [10,] 0.09486 0.00000
## [11,] 0.00000 0.00000
## [12,] 0.18813 0.00000
                                                     18 / 32
```

Alternative setting: Sparse PCA L1 penalty

19 / 32

Sparse PCA data formats

PCA and Sparse PCA procedure can start with any of

data matrix covariance matrix correlation matrix

```
spca(x,K,para,type=c("predictor","Gram"),
sparse=c("penalty","varnum"),
use.corr=FALSE,lambda=1e-6,max.iter=200,
trace=FALSE,eps.conv=1e-3)
```

When using covariance or correlation matrix instead of data matrix, need to specify type = "Gram"

21 / 32

Example 3 corr matrix (cont.)

round(pitprops,1)[1:13,8:13]

```
bowmax bowdist whorls clear knots diaknot
##
## topdiam
              0.4
                      0.6
                                                  0.1
                              0.5
                                    0.1
                                          0.0
                                          0.0
                                                  0.1
              0.4
                      0.6
                              0.6
                                    0.1
## length
## moist
             -0.1
                             -0.1
                                    0.2
                                          0.2
                                                  0.1
## testsg
             -0.1
                      0.1
                              0.0
                                    0.1
                                          0.2
                                                  0.0
                                                 -0.2
              0.0
                      0.0
                                  -0.1
                                         -0.1
## ovensg
                              0.0
                                    0.0
                                          0.0
                                                 -0.3
              0.1
                      0.2
                              0.3
## ringtop
                                 -0.1 -0.2
                      0.5
                                                 -0.4
## ringbut
              0.4
                              0.7
                                         -0.4
## bowmax
              1.0
                      0.5
                                    0.1
                                                 -0.2
## bowdist
              0.5
                      1.0
                              0.5
                                    0.1 - 0.1
                                                 -0.1
              0.6
                      0.5
                              1.0 -0.3 -0.4
                                                 -0.3
## whorls
              0.1
## clear
                      0.1
                             -0.3
                                   1.0
                                         0.0
                                                  0.0
## knots
             -0.4
                     -0.1
                             -0.4
                                    0.0
                                          1.0
                                                  0.2
             -0.2
                     -0.1
                             -0.3
                                    0.0
                                          0.2
                                                  1.0
## diaknot
```

Example 3 - Sparse PCA with correlation matrix

Example 3

Data of pip prop measurements, already in correlation matrix form.

```
# Example of sPCA for correlation matrix
data(pitprops) # 13 input vars corr matrix from 180 obs
round(pitprops,1)[1:10,1:6]
```

```
topdiam length moist testsg ovensg ringtop
## topdiam
               1.0
                       1.0
                             0.4
                                    0.3
                                           -0.1
                                                    0.3
## length
               1.0
                      1.0
                             0.3
                                           -0.1
                                                    0.3
                                    0.3
                      0.3
                                                    0.2
## moist
               0.4
                             1.0
                                    0.9
                                           -0.1
                             0.9
## testsg
               0.3
                      0.3
                                    1.0
                                           0.2
                                                    0.4
## ovensg
              -0.1
                      -0.1
                            -0.1
                                    0.2
                                           1.0
                                                    0.4
                      0.3
                            0.2
                                    0.4
                                                    1.0
## ringtop
               0.3
                                           0.4
                             0.0
                                    0.2
                                                    0.8
## ringbut
               0.5
                      0.5
                                            0.3
                      0.4 - 0.1
                                   -0.1
                                            0.0
                                                    0.1
## bowmax
               0.4
                            0.1
## bowdist
               0.6
                      0.6
                                    0.1
                                            0.0
                                                    0.2
                                                    0.3^{-22/32}
## whorls
               0.5
                      0.6 -0.1
                                    0.0
                                            0.0
```

Example 3 data info

p=13 explanatory var's, n=180 obs on pit prop (mining lumber) The response variables are maximum compressive strength.

TOPDIAM: the top diameter of the prop in inches;

LENGTH: the length of the prop in inches;

MOIST: the moisture content of the prop, expressed as a per

TESTSG: the specific gravity of the timber at the time of 1

OVENSG: the oven-dry specific gravity of the timber;

RINOTOP: the number of annual rings at the top of the prop:

RINGBUT: the number of annual rings at the base of the proj

BowMAx: the maximum bow in inches;

BOWDIST: the distance of the point of maximum bow from the

WHORLS: the number of knot whorls;

CLEAR: the length of clear prop from the top of the prop in

KNOTS: the average number of knots per whorl;

DIAKNOT: the average diameter of the knots in inches.

Example 3 - PCA PCs

round(princomp(covmat=pitprops)\$loadings[,1:6],1)

```
Comp.1 Comp.2 Comp.3 Comp.4 Comp.5 Comp.6
##
## topdiam
             0.4
                    0.2
                           0.2
                                  0.1
                                         0.1
                                                0.1
                                  0.1
                                         0.1
                                                0.2
## length
             0.4
                    0.2
                           0.2
## moist
             0.1
                    0.5
                          -0.1
                                 -0.1
                                        -0.3
                                              -0.3
             0.2
                                        -0.4
                                              -0.1
                    0.5
                          -0.4
                                 -0.1
## testsg
## ovensg
             0.1
                   -0.2
                          -0.5
                                  0.0
                                       -0.2
                                               0.6
## ringtop
             0.3
                    0.0
                          -0.5
                                  0.1
                                         0.3
                                                0.1
                                  0.1
## ringbut
             0.4
                   -0.2
                          -0.3
                                         0.2
                                                0.0
                   -0.2
                           0.2
                                 -0.3 -0.2
                                             -0.1
             0.3
## bowmax
## bowdist
             0.4
                    0.0
                           0.2
                                -0.1
                                         0.1
                                                0.0
                                       -0.2
## whorls
             0.4
                   -0.2
                           0.1
                                  0.2
                                              -0.2
## clear
             0.0
                    0.2
                           0.1 -0.8
                                         0.3
                                                0.2
            -0.1
                    0.3 -0.1
                                  0.3
                                         0.6
                                               -0.2
## knots
## diaknot
            -0.1
                    0.3
                           0.3
                                  0.3 - 0.1
                                                0.6
```

25 / 32

Example 3 - Consider Sparse PCA

- Use correlation matrix directly (type = "Gram")
- Keep track of the progress (trace = TRUE)
- Give the number of principal components desired (K = ...)
- Give the number of non-zero terms in each component (para = c(...,..))

```
## iterations 10
## iterations 20
## iterations 30
## iterations 40
```

Exampe 3 PCA PCs - hard to interpret

A classical example showing the difficulty of interpreting the PC.

```
princomp(covmat=pitprops)$sdev^2/13 # % of PC variance

## Comp.1 Comp.2 Comp.3 Comp.4 Comp.5 Comp.6
## 0.324510 0.182931 0.144479 0.085338 0.070004 0.062724 0.
## Comp.9 Comp.10 Comp.11 Comp.12 Comp.13
## 0.027129 0.014680 0.003890 0.003190 0.002979

sum((princomp(covmat=pitprops)$sdev)^2)

## [1] 13
```

26 / 32

Example 3 Sparse PCA (7,4,4,1,1,1)

```
out0
##
## Call:
## spca(x = pitprops, K = 6, para = c(7, 4, 4, 1, 1, 1), ty
       sparse = "varnum", trace = TRUE)
##
## 6 sparse PCs
## Pct. of exp. var. : 28.2 13.9 13.1 7.4 6.8 6.3
## Num. of non-zero loadings : 7 4 4 1 1 1
## Sparse loadings
##
             PC1
                    PC2
                           PC3 PC4 PC5 PC6
## topdiam -0.477 0.003 0.000
## length -0.469 0.000 0.000
                                         0
## moist
           0.000 0.785 0.000
           0.000 0.619 0.000
## testsg
                                         0
## ovensg
           0.180 0.000
                        0.656
## ringtop 0.000 0.000 0.589
                                                     28 / 32
```

Example 3 Sparse PCA (4,4)

```
spca(pitprops, K=2, type="Gram", sparse="varnum", para=c(4,4))
##
## Call:
## spca(x = pitprops, K = 2, para = c(4, 4), type = "Gram".
##
## 2 sparse PCs
## Pct. of exp. var. : 16.4 15.6
## Num. of non-zero loadings: 44
## Sparse loadings
##
              PC1 PC2
## topdiam 0.000 0.429
## length
           0.000 0.359
## moist
           0.000 0.772
## testsg 0.000 0.300
## ovensg
           0.000 0.000
## ringtop 0.000 0.000
## ringbut -0.792 0.000
                                                      29 / 32
```

Example 3 - Use Sparse PCA L1 penalty

Use correlation matrix, L1 penalty instead of number of element restriction.

Example 3 "Sparse" PCA with all coefficients > 0

The result is equivalent to PCA

```
spca(pitprops, K=9, type="Gram", sparse="varnum",
                       para=rep(13,9))
##
## Call:
## spca(x = pitprops, K = 9, para = rep(13, 9), type = "Grain of type = 
##
## 9 sparse PCs
## Pct. of exp. var. : 32.5 18.3 14.4 8.5 7.0 6.3 4.4
## Num. of non-zero loadings : 13 13 13 13 13 13 13 13
## Sparse loadings
##
                                                               PC1
                                                                                               PC2
                                                                                                                               PC3
                                                                                                                                                                PC4
                                                                                                                                                                                               PC5
                                                                                                                                                                                                                                PC6
                                                                                                                                                                                                                                                                PC7
## topdiam -0.404 0.218 -0.207 0.091 -0.083 0.120 -0.111
## length -0.406 0.186 -0.235 0.103 -0.113 0.163 -0.078
## moist -0.124 0.541 0.141 -0.078 0.350 -0.276 -0.022
## testsg -0.173 0.456 0.352 -0.055 0.356 -0.054 0.079
```

Example 3 - Comparison of para settings

```
out1 # Same as varnum = c(7,4,4,1,1,1)
##
## Call:
## spca(x = pitprops, K = 6, para = c(0.06, 0.16, 0.1, 0.5)
       0.5), type = "Gram", sparse = "penalty", trace = TRI
##
## 6 sparse PCs
## Pct. of exp. var. : 28.0 14.0 13.3 7.4 6.8 6.2
## Num. of non-zero loadings : 7 4 4 1 1 1
## Sparse loadings
             PC1
                    PC2
                           PC3 PC4 PC5 PC6
## topdiam -0.477 0.000 0.000
## length -0.476 0.000 0.000
## moist
           0.000 0.785 0.000
                                         0
## testsg 0.000 0.619 0.000
## ovensg
           0.177 0.000 0.641
                                     0
                                         0
## ringtop 0.000 0.000 0.589
                                                     32 / 32
```