Acrons

Acronis Software-Defined Infrastructure 2.5

Administrator's Command Line Guide

March 26, 2019

Copyright Statement

Copyright ©Acronis International GmbH, 2002-2019. All rights reserved.

"Acronis" and "Acronis Secure Zone" are registered trademarks of Acronis International GmbH.

"Acronis Compute with Confidence", "Acronis Startup Recovery Manager", "Acronis Instant Restore", and the Acronis logo are trademarks of Acronis International GmbH.

Linux is a registered trademark of Linus Torvalds.

VMware and VMware Ready are trademarks and/or registered trademarks of VMware, Inc. in the United States and/or other jurisdictions.

Windows and MS-DOS are registered trademarks of Microsoft Corporation.

All other trademarks and copyrights referred to are the property of their respective owners.

Distribution of substantively modified versions of this document is prohibited without the explicit permission of the copyright holder.

Distribution of this work or derivative work in any standard (paper) book form for commercial purposes is prohibited unless prior permission is obtained from the copyright holder.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Third party code may be provided with the Software and/or Service. The license terms for such third-parties are detailed in the license.txt file located in the root installation directory. You can always find the latest up-to-date list of the third party code and the associated license terms used with the Software and/or Service at http://kb.acronis.com/content/7696

Acronis patented technologies

Technologies, used in this product, are covered and protected by one or more U.S. Patent Numbers: 7,047,380; 7,246,211; 7,275,139; 7,281,104; 7,318,135; 7,353,355; 7,366,859; 7,383,327; 7,475,282; 7,603,533; 7,636,824; 7,650,473; 7,721,138; 7,779,221; 7,831,789; 7,836,053; 7,886,120; 7,895,403; 7,934,064; 7,937,612; 7,941,510; 7,949,635; 7,953,948; 7,979,690; 8,005,797; 8,051,044; 8,069,320; 8,073,815; 8,074,035; 8,074,276; 8,145,607; 8,180,984; 8,225,133; 8,261,035; 8,296,264; 8,312,259; 8,347,137; 8,484,427; 8,645,748; 8,732,121; 8,850,060; 8,856,927; 8,996,830; 9,213,697; 9,400,886; 9,424,678; 9,436,558; 9,471,441; 9,501,234; and patent pending applications.

Contents

1.	Intro	duction		1
	1.1	Providi	ng Credentials	2
	1.2	Manag	ing Tasks	2
2.	Mana	aging St	orage Cluster	4
	2.1	Manag	ing Tokens	4
		2.1.1	vinfra node token show	4
		2.1.2	vinfra node token create	4
		2.1.3	vinfra node token validate	5
	2.2	Manag	ing Traffic Types and Networks	5
		2.2.1	vinfra cluster traffic-type create	5
		2.2.2	vinfra cluster traffic-type list	6
		2.2.3	vinfra cluster traffic-type show	7
		2.2.4	vinfra cluster traffic-type set	7
		2.2.5	vinfra cluster traffic-type delete	8
		2.2.6	vinfra cluster network create	8
		2.2.7	vinfra cluster network list	9
		2.2.8	vinfra cluster network show	9
		2.2.9	vinfra cluster network set	0
		2.2.10	vinfra cluster network set-bulk	1
		2.2.11	vinfra cluster network delete	2
	2.3	Manag	ing Storage Nodes	2
		2.3.1	vinfra node join	2
		2.3.2	vinfra node list	4
		2.3.3	vinfra node show	5
		2.3.4	vinfra node release	
		2.3.5	vinfra node forget	

	2.4	Manag	ing Node Network Interfaces
		2.4.1	vinfra node network iface list
		2.4.2	vinfra node network iface show
		2.4.3	vinfra node network iface
		2.4.4	vinfra node network iface set
		2.4.5	vinfra node network bond create
		2.4.6	vinfra node network bond delete
		2.4.7	vinfra node network vlan create
		2.4.8	vinfra node network vlan delete
	2.5	Manag	ing Node Disks
		2.5.1	vinfra node disk list
		2.5.2	vinfra node disk show
		2.5.3	vinfra node disk assign
		2.5.4	vinfra node disk release
		2.5.5	vinfra node disk blink
		2.5.6	vinfra node iscsi target add
		2.5.7	vinfra node iscsi target delete
	2.6	vinfra c	luster create
	2.7	Showin	g Storage Cluster Overview and Details
		2.7.1	vinfra cluster overview
		2.7.2	vinfra cluster show
	2.8	vinfra o	luster delete
3.	Mana	nging Co	empute Cluster
	3.1	vinfra s	service compute cluster create
	3.2		g Compute Cluster Details and Overview
		3.2.1	vinfra service compute cluster show
		3.2.2	vinfra service compute cluster stat
	3.3	vinfra s	service compute cluster set
	3.4	Managi	ing Compute Nodes
		3.4.1	vinfra service compute node add
		3.4.2	vinfra service compute node list
		3.4.3	Showing Compute Node Details
		3.4.4	vinfra service compute node fence
		3.4.5	vinfra service compute node unfence
		3.4.6	vinfra service compute node release

3.5	Manag	ing Networks
	3.5.1	vinfra service compute network create
	3.5.2	vinfra service compute network list
	3.5.3	vinfra service compute network show
	3.5.4	vinfra service compute network set
	3.5.5	vinfra service compute network delete
3.6	Manag	ing Images
	3.6.1	vinfra service compute image create
	3.6.2	vinfra service compute image list 57
	3.6.3	vinfra service compute image show
	3.6.4	vinfra service compute image set
	3.6.5	vinfra service compute image save
	3.6.6	vinfra service compute image delete
3.7	Manag	ing Flavors
	3.7.1	vinfra service compute flavor create
	3.7.2	vinfra service compute flavor list
	3.7.3	vinfra service compute flavor show
	3.7.4	vinfra service compute flavor delete
3.8	Manag	ing Storage Policies
	3.8.1	vinfra cluster storage-policy create
	3.8.2	vinfra cluster storage-policy list
	3.8.3	vinfra cluster storage-policy show
	3.8.4	vinfra cluster storage-policy set
	3.8.5	vinfra cluster storage-policy delete
3.9	Manag	ing Volumes
	3.9.1	vinfra service compute volume create
	3.9.2	vinfra service compute volume list
	3.9.3	vinfra service compute volume show
	3.9.4	vinfra service compute volume set
	3.9.5	vinfra service compute volume extend
	3.9.6	vinfra service compute server volume attach
	3.9.7	vinfra service compute server volume detach
	3.9.8	vinfra service compute volume delete
3.10	Manag	ing Virtual Machines
	3.10.1	vinfra service compute server create

		3.10.2	vintra service compute server list	/4
		3.10.3	vinfra service compute server show	74
		3.10.4	vinfra service compute server stat	75
		3.10.5	vinfra service compute server iface attach	76
		3.10.6	vinfra service compute server iface list	77
		3.10.7	vinfra service compute server iface detach	77
		3.10.8	vinfra service compute server log	78
		3.10.9	vinfra service compute server migrate	78
		3.10.10	vinfra service compute server resize	79
		3.10.11	vinfra service compute server start	79
		3.10.12	vinfra service compute server pause	79
		3.10.13	vinfra service compute server unpause	80
		3.10.14	vinfra service compute server suspend	80
		3.10.15	vinfra service compute server resume	81
		3.10.16	vinfra service compute server reboot	81
		3.10.17	vinfra service compute server reset-state	81
		3.10.18	vinfra service compute server stop	82
		3.10.19	vinfra service compute server evacuate	82
		3.10.20	vinfra service compute server delete	83
	3.11	vinfra s	ervice compute cluster delete	83
				_
4.		_	neral Settings	
	4.1	O	ng Licenses	
		4.1.1	vinfra cluster license load	
		4.1.2	vinfra cluster license show	
	4.2	Managi	ng Users	85
		4.2.1	vinfra cluster user list-available-roles	85
		4.2.2	vinfra cluster user create	86
		4.2.3	vinfra cluster user list	87
		4.2.4	vinfra cluster user show	87
		4.2.5	vinfra cluster user set	88
		4.2.6	vinfra cluster user change-password	89
		4.2.7	vinfra cluster user delete	89
	4.3	Managi	ng SSH Keys	90
		4.3.1	vinfra cluster sshkey add	
		4.3.2	vinfra cluster sshkey list	

		4.3.3	vinfra cluster sshkey delete				
	4.4 Managing External DNS Servers						
		4.4.1	vinfra cluster settings dns show				
		4.4.2	vinfra cluster settings dns set				
	4.5	Configu	uring Management Node High Availability 93				
		4.5.1	vinfra cluster ha create				
		4.5.2	vinfra cluster ha join				
		4.5.3	vinfra cluster ha show				
		4.5.4	vinfra cluster ha release				
	4.6	Manag	ing Storage Tier Encryption				
		4.6.1	vinfra cluster settings encryption show				
		4.6.2	vinfra cluster settings encryption set				
	4.7	Manag	ing Alerts				
		4.7.1	vinfra cluster alert list				
		4.7.2	vinfra cluster alert show				
		4.7.3	vinfra cluster alert delete				
	4.8	8 Managing Audit Log					
		4.8.1	vinfra cluster auditlog list				
		4.8.2	vinfra cluster auditlog show				
	4.9	vinfra c	cluster problem-report				
5.	Moni	toring S	itorage Cluster				
	5.1	Monito	ring General Storage Cluster Parameters				
	5.2	Monito	ring Metadata Servers				
	5.3	Monito	ring Chunk Servers				
		5.3.1	Understanding Disk Space Usage				
			5.3.1.1 Understanding Allocatable Disk Space				
			5.3.1.2 Viewing Space Occupied by Data Chunks				
		5.3.2	Exploring Chunk States				
	5.4	Monito	ring Clients				
	5.5	Monito	ring Physical Disks				
	5.6	Monito	ring Event Logs				
	5.7	Monito	ring Replication Parameters				
6.	Acces	ssing Sto	orage Clusters via iSCSI				
	6.1	iSCSI W	/orkflow Overview				

6.2	Config	uring CLI Tool	124			
6.3	Manag	ging Target Groups	125			
	6.3.1	Creating Target Groups	125			
	6.3.2	Starting and Stopping Target Groups	127			
	6.3.3	Listing Target Groups	127			
	6.3.4	Printing Details of Target Groups	128			
	6.3.5	Deleting Target Groups	128			
6.4	Managing iSCSI Volumes					
	6.4.1	Creating iSCSI Volumes	128			
	6.4.2	Listing and Printing Details of iSCSI Volumes	129			
	6.4.3	Attaching iSCSI Volumes to Target Groups	129			
	6.4.4	Viewing and Setting iSCSI Volume Parameters	129			
	6.4.5	Increasing iSCSI Volume Size	130			
	6.4.6	Setting iSCSI Volume Limits	130			
	6.4.7	Detaching iSCSI Volumes from Target Groups	130			
	6.4.8	Deleting iSCSI Volumes	130			
6.5	Manag	ging Nodes	131			
	6.5.1	Adding Nodes to Target Groups	131			
	6.5.2	Setting Node Status	132			
	6.5.3	Deleting Nodes from Target Groups	132			
6.6	Manag	ging Targets and Portals	133			
	6.6.1	Creating Targets	133			
	6.6.2	Adding and Removing Target Portals	133			
	6.6.3	Deleting Targets	134			
6.7	Manag	ging CHAP Accounts	134			
	6.7.1	Creating and Listing CHAP Accounts	134			
	6.7.2	Changing CHAP Account Details	135			
	6.7.3	Assigning CHAP Accounts to Target Groups	135			
	6.7.4	Deleting CHAP Accounts	135			
6.8	Manag	ging LUN Views	135			
	6.8.1	Creating LUN Views	136			
	6.8.2	Listing LUN Views	136			
	6.8.3	Changing LUN View Details	136			
	6.8.4	Deleting LUN Views	137			
A dva	need Ta	agles.	120			

7.1	Updating Kernel with ReadyKernel						
	7.1.1	Installing ReadyKernel Patches Automatically					
	7.1.2	Managin	g ReadyKernel Patches Manually				
		7.1.2.1	Dowloading, Installing, and Loading ReadyKernel Patches				
		7.1.2.2	Loading and Unloading ReadyKernel Patches				
		7.1.2.3	Installing and Removing ReadyKernel Patches for Specific Kernels				
		7.1.2.4	Downgrading ReadyKernel Patches				
		7.1.2.5	Disabling Loading of ReadyKernel Patches on Boot				
		7.1.2.6	Managing ReadyKernel Logs				
7.2	Managing Guest Tools						
	7.2.1	Installing	g Guest Tools				
		7.2.1.1	Installing Guest Tools in New VMs				
		7.2.1.2	Installing Guest Tools in Existing VMs				
	7.2.2	Uninstal	ling Guest Tools				
		7.2.2.1	Uninstalling Guest Tools from Linux VMs				
		7.2.2.2	Uninstalling Guest Tools from Windows VMs145				
7.3	Runnin	ig Comma	nds in Virtual Machines without Network Connectivity				
	7.3.1	Running Commands in Linux Virtual Machines					
	7.3.2	Running Commands in Windows Virtual Machines					
7.4	Setting	Virtual M	achines CPU Model				
7.5	Creatin	ng Linux Te	emplates				
7.6	Securir	ng OpenSt	rack API Traffic with SSL				
7.7	Enablir	ng Backup	Gateway Geo-Replication				

CHAPTER 1

Introduction

This guide describes the syntax and parameters of the vinfra command-line tool that can be used to manage Acronis Software-Defined Infrastructure from console and automate such management tasks.

Note: While the following chapters provide a reference of specific operations that you can perform with vinfra, you can also run vinfra help to get a list of all supported commands and their descriptions. For help on a specific command, either run vinfra help <command> or vinfra <command> --help.

In addition, this guide describes how to use the command line to perform operations unsupported by vinfra as of now.

Note that the following operations should not be done from the command line:

- setting custom paths for Acronis Software-Defined Infrastructure services, in particular:
 - creating S3 clusters only in /mnt/vstorage/vols/s3,
 - creating iSCSI targets only in /mnt/vstorage/vols/iscsi,
- · mounting clusters or change cluster mount options,
- configuring firewall with firewall-cmd,
- · renaming network connections,
- managing MDS/CS,
- · managing partitions, LVMs, or software RAID,
- modifying files in /mnt/vstorage/vols and /mnt/vstorage/webcp/backup directories,

• setting encoding or replication of cluster root.

1.1 Providing Credentials

The vinfra CLI tool requires the following information to be used:

- IP address or hostname of the management node (set to backend-api.svc.vstoragedomain by default).
- Username (admin by default).
- Password (created during installation of Acronis Software-Defined Infrastructure).

This information can be supplied via the --vinfra-portal, --vinfra-username, and --vinfra-password command-line parameters with each command. Alternatively, you can supply it by setting the environment variables VINFRA_PORTAL, VINFRA_USERNAME, and VINFRA_PASSWORD (e.g., in your ~/.bash_profile). In this case, you will be able to run the CLI tool without the aforementioned command-line parameters.

As you typically run vinfra from the management node as admin, the only variable you usually need to set is the password. For example:

```
# export VINFRA_PASSWORD=12345
```

If you installed vinfra on a remote machine and/or run it as a different user, you will need to set VINFRA_PORTAL and/or VINFRA_USERNAME on that machine in addition to VINFRA_PASSWORD.

1.2 Managing Tasks

The vinfra CLI tool executes some commands immediately, while for other commands (that may take some time to complete) it creates system tasks that are queued. Examples of actions performed via tasks are creating the storage or compute cluster and adding nodes to it.

To keep track of tasks being performed by vinfra, use the vinfra task list and vinfra task show commands. For example:

CHAPTER 2

Managing Storage Cluster

2.1 Managing Tokens

2.1.1 vinfra node token show

Display the backend token:

```
usage: vinfra node token show
```

Example:

This command shows the details of the current token.

2.1.2 vinfra node token create

Create the backend token:

```
usage: vinfra node token create [--ttl <ttl>]
```

--ttl <ttl>

Token TTL, in seconds

Example:

This command creates a new token with the time to live (TTL) of 86400 seconds.

2.1.3 vinfra node token validate

Validate the backend token:

```
usage: vinfra node token validate <token>
<token>
```

Token value

Example:

```
# vinfra node token validate dc56d4d2
+-----+
| Field | Value |
+-----+
| status | valid |
+-----+
```

This command validates the token dc56d4d2.

2.2 Managing Traffic Types and Networks

2.2.1 vinfra cluster traffic-type create

Create a new traffic type:

```
usage: vinfra cluster traffic-type create --port <port> <traffic-type-name>
--port <port>
```

Traffic type port

<traffic-type-name>

Traffic type name

Example:

This command creates a custom traffic type MyTrafficType on port 6900.

2.2.2 vinfra cluster traffic-type list

List available traffic types:

```
usage: vinfra cluster traffic-type list
```

Example:

<pre># vinfra cluster traffic-type list +</pre>						
name +						
Storage Internal management OSTOR private S3 public iSCSI NFS ABGW private ABGW public Admin panel SSH VM public VM private Compute API MyTrafficType						

This command lists all traffic types in Acronis Software-Defined Infrastructure.

2.2.3 vinfra cluster traffic-type show

Show details of a traffic type:

```
usage: vinfra cluster traffic-type show <traffic-type>
<traffic-type>
    Traffic type name
```

Example:

This command shows the details of the traffic type Storage.

2.2.4 vinfra cluster traffic-type set

Modify traffic type parameters:

```
usage: vinfra cluster traffic-type set [--name <name>] [--port <port>] <traffic-type>

--name <name>
        A new name for the traffic type

--port <port>
        A new port for the traffic type

<traffic-type>
        Traffic type name
```

This command renames the traffic type MyTrafficType to MyOtherTrafficType and changes its port to 6901.

2.2.5 vinfra cluster traffic-type delete

Delete a traffic type:

```
usage: vinfra cluster traffic-type delete <traffic-type>
```

<traffic-type>

Traffic type name

Example:

```
# vinfra cluster traffic-type delete "MyOtherTrafficType"
Operation successful
```

This command deletes the custom traffic type MyOtherTrafficType.

2.2.6 vinfra cluster network create

Create a new network:

```
usage: vinfra cluster network create [--traffic-types <traffic-types>] <network-name>
```

--traffic-types <traffic-types>

A comma-separated list of traffic type IDs or names

<network-name>

Network name

```
+-----+
```

This command creates a custom network MyNet and assigns the traffic type SSH to it.

2.2.7 vinfra cluster network list

List available networks:

```
usage: vinfra cluster network list
```

Example:

# vinfra cluster network list								
 id +	name +	roles +						
358bdc39-cd8b-4565-8ebf-e7c12dcd1cf7 	Public 	- ABGW public - iSCSI - NFS - S3 public - SSH - Admin Panel						
6095a997-e5f1-493d-a750-41ddf277153b 	 Private 							

This command lists all networks in Acronis Software-Defined Infrastructure.

2.2.8 vinfra cluster network show

Show details of a network:

```
usage: vinfra cluster network show <network>
```

<network>

Network ID or name

```
# vinfra cluster network show MyNet
+-----+
| Field | Value
+-----+
```

This command shows the details of the custom network MyNet.

2.2.9 vinfra cluster network set

Modify network parameters:

```
usage: vinfra cluster network set [--name <network-name>]
[--traffic-types <traffic-types> |
--add-traffic-types <traffic-types> |
--del-traffic-types <traffic-types>]
<network>
```

--name <network-name>

Network name

--traffic-types <traffic-types>

A comma-separated list of traffic type names (overwrites network's current traffic types)

--add-traffic-types <traffic-types>

A comma-separated list of traffic type names (adds the specified traffic types to the network)

--del-traffic-types <traffic-types>

A comma-separated list of traffic type names (removes the specified traffic types from the network)

<network>

Network ID or name

Example:

This command creates a task to rename the network MyNet to MyOtherNet and assign to it the traffic types iscsI and NFS.

Task outcome:

```
# vinfra task show b29f6f66-37d7-47de-b02e-9f4087ad932b
 Field | Value
  ._____+__+
 args | - 03d5eeb3-1833-4626-885d-dd066635f5de
 kwargs | name: MyOtherNet
         | roles:
         | - ssh
         | - iscsi
         | - nfs
         | backend.presentation.network.roles.tasks.RolesSetChangeTask
 name
 result | id: 03d5eeb3-1833-4626-885d-dd066635f5de
         | name: MyOtherNet
         | roles:
         | - iSCSI
         | - NFS
         I - SSH
         | type: Custom
 state
         success
 task_id | b29f6f66-37d7-47de-b02e-9f4087ad932b
```

2.2.10 vinfra cluster network set-bulk

Modify traffic types of multiple networks:

```
usage: vinfra cluster network set-bulk --network <network>:<traffic-types>
```

--network <network>:<traffic-types>

Network configuration in the format:

- <network>: network ID or name;
- <traffic-types>: a comma-separated list of traffic type names;

(this option can be used multiple times).

Example:

This command creates a task to change the traffic type set of the network MyNet1 to SNMP and that of MyNet2 to SSH and SNMP.

Task outcome:

```
# vinfra task show c774f55d-c45b-42cd-ac9e-16fc196e9283
         | Value
 Field
 details |
         | backend.presentation.network.roles.tasks.RolesSetBulkChangeTask
 result | - id: adf49487-9deb-4180-bb0c-08a906257981
             name: MyNet1
             roles:
              - SNMP
             type: Custom
            - id: 3f6ff4a3-31bc-440b-a36f-d755c80d5932
              name: MyNet2
             roles:
              - SNMP
              - SSH
             type: Custom
          success
 state
 task_id | c774f55d-c45b-42cd-ac9e-16fc196e9283
```

2.2.11 vinfra cluster network delete

Delete a network:

```
usage: vinfra cluster network delete <network>
```

<network>

Network ID or name

Example:

```
# vinfra cluster network delete MyOtherNet
Operation successful
```

This command deletes the network MyOtherNet.

2.3 Managing Storage Nodes

2.3.1 vinfra node join

Join a node to the storage cluster:

```
usage: vinfra node join [--disk <disk>:<role>[:<key=value,...>]] <node>
```

```
--disk <disk>:<role> [:<key=value,...>]
```

Disk configuration in the format:

- <disk>: disk device ID or name;
- <role>: disk role (cs, mds, journal, mds-journal, mds-system, cs-system, system);
- comma-separated key=value pairs with keys (optional):
 - tier: disk tier (0, 1, 2 or 3);
 - journal-tier: journal (cache) disk tier (0, 1, 2 or 3);
 - journal-type: journal (cache) disk type (no_cache, inner_cache or external_cache);
 - journal-disk: journal (cache) disk ID or device name;
 - journal-size: journal (cache) disk size, in bytes;
 - bind-address: bind IP address for the metadata service.

E.g., sda:cs:tier=0, journal-type=inner_cache. This option can be used multiple times.

<node>

Node ID or hostname

Example:

```
# vinfra node join f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4 \
--disk sda:mds-system \
--disk sdb:cs \
--disk sdc:cs
+-----+
| Field | Value |
+-----+
| task_id | a2713068-9544-4ea1-8ec8-69a068cf86f2 |
+-----+
```

This command creates a task to add the node with the ID f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4 to the storage cluster and assigns roles to disks: mds-system to sda, cs to sdb' and sdc.

Task outcome:

```
# vinfra task show a2713068-9544-4ea1-8ec8-69a068cf86f2
+------
| Field | Value
| +------+
```

```
| - f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
args
kwargs | disks:
        | - id: 85F32403-94A9-465A-9E6C-C1A2B41294FC
            role: mds-system
            service_params: {}
          - id: FE0B5876-E054-489B-B0FD-72429BEFD46A
            role: cs
            service_params: {}
          - id: D3BEF4BB-AA3B-4DB6-9376-BC7CDA636700
            role: cs
            service_params: {}
name
        | backend.tasks.node.AddNodeInClusterTask
result | {}
state | success
task_id | a2713068-9544-4ea1-8ec8-69a068cf86f2
```

2.3.2 vinfra node list

List storage nodes:

```
usage: vinfra node list
```

Example:

# vinfra node list								
id	host	is_primary	is_online	is_assigned	is_in_ha			
09bb6b84-70a5-41ae-b342- 23e5fc7cc126		True 	True	True 	 False			
187edb11-38c5-487b-bd7f- 57b0fa4b733c	node002.<> 	 False 	True	True	False 			
e6255aed-d6e7-41b2-ba90- 86164c1cd9a6	node003.<>	False 	True	True	False 			
+	+	+	·	t	++			

This command lists all nodes registered in Acronis Software-Defined Infrastructure (both unassigned and used in the storage cluster).

2.3.3 vinfra node show

Show storage node details:

```
usage: vinfra node show <node>
```

<node>

Node ID or hostname

Example:

```
# vinfra node show 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
               | Value
 Field
 cpu_cores | 2
host | stor-1.example.com.vstoragedomain.
             | 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
| id
 ipaddr
             | stor-1.example.com.vstoragedomain.
| is_assigned | False
| is_in_ha | False
| is_installing | False
| is_online
             | True
| is_primary
               | True
 is_virt
               | True
               8201310208
 mem_total
               | management:
 roles
                  is_primary: true
 tasks
```

This command show the details of the node with the ID 4f96acf5-3bc8-4094-bcb6-4d1953be7b55.

2.3.4 vinfra node release

Release a node from the storage cluster. Start data migration from the node as well as cluster replication and rebalancing to meet the configured redundancy level:

```
usage: vinfra node release [--force] <node>
```

--force

Release node without data migration

<node>

Node ID or hostname

Example:

This command creates a task to release the node with the ID f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4 from the storage cluster with migration of data to maintain the set redundancy mode.

Task outcome:

2.3.5 vinfra node forget

Remove a node from the storage cluster:

```
usage: vinfra node forget <node>
```

<node>

Node ID or hostname

Example:

This commands creates a task to unregister the node with the ID fd1e46de-6e17-4571-bf6b-1ac34ec1c225 from Acronis Software-Defined Infrastructure.

Task outcome:

2.4 Managing Node Network Interfaces

2.4.1 vinfra node network iface list

List node network interfaces:

```
usage: vinfra node network iface list (-a | --node <node>)

-a, --all
    List all network interfaces on all nodes

--node <node>
    Node ID or hostname to list network interfaces on
```

Example:

This command shows network interfaces of the node with the ID 4f96acf5-3bc8-4094-bcb6-4d1953be7b55.

2.4.2 vinfra node network iface show

Show details of a network interface:

```
usage: vinfra node network iface show --node <node> <iface>
```

--node <node>

Node ID or hostname

<iface>

Network interface name

Example:

```
# vinfra node network iface show eth0 --node 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
                   | Value
| Field
| contained_in
                  10.94.29.218
| dhcp4
| dhcp4_enabled | True
| dhcp6
                  | fe80::21c:42ff:fe2a:4fdf
| dhcp6_enabled
                  | True
                   | - 127.0.0.1
I dns4
I dns6
| duplex
                  | 10.94.0.1
| gw4
gw6
| ignore_auto_routes_v4 | False
| ignore_auto_routes_v6 | False
       | - 10.94.29.218/16
| ipv4
                  | - fe80::21c:42ff:fe2a:4fdf/64
| ipv6
| mac_addr
               | 00:1c:42:2a:4f:df
| mtu
                   | 1500
                  | True
| multicast
                  | eth0
| name
                  | 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
| True
| node_id
| plugged
| roles_set
                  | 237e58dd-6c10-49c1-be7f-7ddf7de2efd1
| rx_bytes
                  | 1844502614
| rx_dropped
                  0
                   | 0
| rx_errors
| rx_overruns
                  | 11543284
| rx_packets
                  current: null
speeds
                   | max: null
state
                  | up
                   28477979
| tx_bytes
                   0
| tx_dropped
| tx_errors
                   1 0
| tx_overruns
                  | 0
tx_packets
                   | 107649
                   | iface
 type
```

This command shows the details of the network interface etho located on the node with the ID

4f96acf5-3bc8-4094-bcb6-4d1953be7b55.

2.4.3 vinfra node network iface

Bring a network interface up:

```
usage: vinfra node network iface up --node <node> <iface>
```

--node <node>

Node ID or hostname

<iface>

Network interface name

Bring a network interface down:

```
usage: vinfra node network iface down --node <node> <iface>
```

--node <node>

Node ID or hostname

<iface>

Network interface name

```
# vinfra node network iface up eth2 --node 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
                    | Value
| Field
| contained_in
| dhcp4
                    | 10.37.130.138
| dhcp4_enabled
                    | True
 dhcp6
                    | fe80::21c:42ff:fef8:5b90
| dhcp6_enabled
                    | True
| dns4
                     | - 127.0.0.1
                     1 []
| dns6
 duplex
| gw4
                     | 10.94.0.1
| gw6
ignore_auto_routes_v4 | False
 ignore_auto_routes_v6 | False
 ipv4
                     | - 10.37.130.138/24
 ipv6
                     | - fe80::21c:42ff:fef8:5b90/64
 mac_addr
                     | 00:1c:42:f8:5b:90
```

```
mtu
                      | 1500
 multicast
                      | True
                      | eth2
| name
                      | 4f96acf5-3bc8-4094-bcb6-4d1<u>953be7b55</u>
| node_id
| plugged
| roles_set
                     97632
| rx_bytes
| rx_dropped
                      | 0
                      0
| rx_errors
| rx_overruns
                     | 0
| rx_packets
                     | 1258
speeds
                     | current: null
                     | max: null
state
                     | up
| tx_bytes
                      | 1116
                     | 0
| tx_dropped
                     1 0
| tx_errors
| tx_overruns
                      | 0
| tx_packets
                      | 8
                      | iface
```

This commands brings up the network interface eth2 located on the node with the ID 4f96acf5-3bc8-4094-bcb6-4d1953be7b55.

```
# vinfra node network iface down eth2 --node 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
                     | Value
| Field
| contained_in
| dhcp4
| dhcp4_enabled | True
| dhcp6
| dhcp6_enabled
                    | True
| dns4
                     | - 127.0.0.1
| dns6
| duplex
                    | 10.94.0.1
gw4
| gw6
| ignore_auto_dns_v4 | False
| ignore_auto_routes_v4 | False
| ignore_auto_routes_v6 | False
| ipv4
                     | ipv6
                     []
                    | 00:1c:42:f8:5b:90
| mac_addr
| mtu
                     | 1500
| multicast
                     | True
| name
                     | 4f96acf5-3bc8-4094-bcb6-4d1<u>953be7b55</u>
| node_id
| plugged
                     | False
| roles_set
```

```
rx_bytes
                       | 97984
                       0
 rx_dropped
                       | 0
 rx_errors
rx_overruns
                       1 0
 rx_packets
                       1 1264
                       | current: null
 speeds
                       | max: null
state
                       | down
tx_bytes
                       | 1116
                       1 0
| tx_dropped
tx_errors
                       1 0
                       1 0
 tx_overruns
 tx_packets
                       | 8
 type
                       | iface
```

This commands brings down the network interface eth2 located on the node with the ID 4f96acf5-3bc8-4094-bcb6-4d1953be7b55.

2.4.4 vinfra node network iface set

Modify network interface parameters (overwrites omitted options to interace default values):

```
--ipv4 <ipv4>
A comma-separated list of IPv4 addresses

--ipv6 <ipv6>
A comma-separated list of IPv6 addresses

--gw4 <gw4>
Gateway IPv4 address

--gw6 <gw6>
Gateway IPv6 address

--mtu <mtu>
MTU interface value
```

```
--dhcp4
     Enable DHCPv4
--no-dhcp4
     Disable DHCPv4
--dhcp6
     Enable DHCPv6
--no-dhcp6
     Disable DHCPv6
--auto-routes-v4
     Enable automatic IPv4 routes
--ignore-auto-routes-v4
     Ignore automatic IPv4 routes
--auto-routes-v6
     Enable automatic IPv6 routes
--ignore-auto-routes-v6
     Ignore automatic IPv6 routes
--network <network>
     Network ID or name
--connected-mode
     Enable connected mode (InfiniBand interfaces only)
--datagram-mode
     Enable datagram mode (InfiniBand interfaces only)
--node <node>
     Node ID or hostname
<iface>
     Network interface name
Example:
 # vinfra node network iface set eth2 --network Private \
 --node 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
```

```
| Field | Value
+-----+
| task_id | 8a378098-6760-4fe9-ac20-1f18a8ed9d2e |
+-----+
```

This command creates a task to assign the network interface eth2 located on the node with the ID 4f96acf5-3bc8-4094-bcb6-4d1953be7b55 to the network Private.

Task outcome:

```
# vinfra task show 8a378098-6760-4fe9-ac20-1f18a8ed9d2e
| Field
          | Value
          | - 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
args
          | - eth2
 kwargs | roles_set: 6095a997-e5f1-493d-a750-41ddf277153b
          | backend.presentation.network.tasks.NetworkInterfaceChangeTask
 result | contained_in: null
          | dhcp4: null
          | dhcp4_enabled: false
          | dhcp6: null
          | dhcp6_enabled: false
          | duplex: null
          | gw4: null
          | gw6: null
          | ignore_auto_routes_v4: true
          | ignore_auto_routes_v6: true
          | ipv4:
          | - 10.37.130.103/24
          | ipv6:
          | - fe80::21c:42ff:fe75:7c4d/64
          | mac_addr: 00:1c:42:75:7c:4d
          | mtu: 1500
          | multicast: true
          | name: eth2
          | node_id: 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
          | plugged: true
          | roles_set: 6095a997-e5f1-493d-a750-41ddf277153b
          | rx_bytes: 38156
          | rx_dropped: 0
          | rx_errors: 0
          | rx_overruns: 0
          | rx_packets: 225
          | speeds:
              current: null
             max: null
          | state: up
          | tx_bytes: 13087
          | tx_dropped: 0
          | tx_errors: 0
          | tx_overruns: 0
```

```
| | tx_packets: 145
| | type: iface |
| state | success |
| task_id | 8a378098-6760-4fe9-ac20-1f18a8ed9d2e |
+------
```

2.4.5 vinfra node network bond create

Create a network bonding:

```
usage: vinfra node network bond create [--ipv4 <ipv4>] [--ipv6 <ipv6>] [--gw4 <gw4>]
                                      [--gw6 <gw6>] [--mtu <mtu>] [--dhcp4 | --no-dhcp4]
                                      [--dhcp6 | --no-dhcp6] [--network <network>]
                                      [--auto-routes-v4 | --ignore-auto-routes-v4]
                                      [--auto-routes-v6 | --ignore-auto-routes-v6]
                                      [--bonding-opts <bonding_opts>] --node <node>
                                      --bond-type <bond-type> --ifaces <ifaces>
--ipv4 <ipv4>
     A comma-separated list of IPv4 addresses
--ipv6 <ipv6>
     A comma-separated list of IPv6 addresses
--gw4 < gw4 >
     Gateway IPv4 address
--gw6 <gw6>
     Gateway IPv6 address
--mtu <mtu>
     MTU interface value
--dhcp4
     Enable DHCPv4
--no-dhcp4
     Disable DHCPv4
--dhcp6
     Enable DHCPv6
--no-dhcp6
     Disable DHCPv6
```

```
--auto-routes-v4
     Enable automatic IPv4 routes
--ignore-auto-routes-v4
     Ignore automatic IPv4 routes
--auto-routes-v6
     Enable automatic IPv6 routes
--ignore-auto-routes-v6
     Ignore automatic IPv6 routes
--network <network>
     Network ID or name
--bonding-opts <bonding_opts>
     Additional bonding options
--bond-type <bond-type>
     Bond type (balance-rr, active-backup, balance-xor, broadcast, 802.3ad, balance-tlb, balance-alb)
--node <node>
     Node ID or hostname
--ifaces <ifaces>
     A comma-separated list of network interface names, e.g., iface1,iface2,...,iface<N>
```

Example:

This command creates a task to bond network interfaces eth2 and eth3 into bond0 of the type balance-xor on the node with the ID fd1e46de-6e17-4571-bf6b-1ac34ec1c225.

Task outcome:

```
# vinfra task show becf96ad-9e39-4bec-b82c-4e1219a196de
+------+
| Field | Value
+-----+
```

```
- fd1e46de-6e17-4571-bf6b-1ac34ec1c225
kwargs | bond_type: balance-xor
        | ifaces:
        | - eth2
         | - eth3
        | registration_token: 3102ed1a
        | backend.presentation.network.tasks.NetworkInterfaceCreateBondingTask
name
result | bond_type: balance-xor
        | dhcp4: 10.37.130.117
        | dhcp4_enabled: true
        | dhcp6: fe80::21c:42ff:fe81:27d0
        | dhcp6_enabled: true
        | duplex: null
        | gw4: 10.94.0.1
        | gw6: null
        | ignore_auto_routes_v4: false
        | ignore_auto_routes_v6: false
        | ipv4:
        | - 10.37.130.117/24
        | ipv6:
        | - fe80::21c:42ff:fe81:27d0/64
        | mac_addr: 00:1c:42:81:27:d0
        | mtu: 1500
        | multicast: true
        | name: bond0
        | node_id: fd1e46de-6e17-4571-bf6b-1ac34ec1c225
        | plugged: true
        | roles_set: ''
        | rx_bytes: 3048
        | rx_dropped: 0
        | rx_errors: 0
        | rx_overruns: 0
        | rx_packets: 22
        | speeds:
            current: null
           max: null
          state: up
        | tx_bytes: 1782
        | tx_dropped: 0
        | tx_errors: 0
        | tx_overruns: 0
        | tx_packets: 13
        | type: bonding
state
        success
task_id | becf96ad-9e39-4bec-b82c-4e1219a196de
```

2.4.6 vinfra node network bond delete

Delete a network bonding:

Network interface name

```
usage: vinfra node network bond delete --node <node> <iface>

--node <node>
    Node ID or hostname
<iface>
```

Example:

This command creates a task to delete the bond bond0 from the node with the ID fd1e46de-6e17-4571-bf6b-1ac34ec1c225.

Task outcome:

2.4.7 vinfra node network vlan create

Create a VLAN:

```
usage: vinfra node network vlan create [--ipv4 <ipv4>] [--ipv6 <ipv6>] [--gw4 <gw4>]
[--gw6 <gw6>] [--mtu <mtu>] [--dhcp4 | --no-dhcp4]
[--dhcp6 | --no-dhcp6] [--network <network>]
[--auto-routes-v4 | --ignore-auto-routes-v4]
[--auto-routes-v6 | --ignore-auto-routes-v6]
```

--node <node> --iface <iface> --tag <tag>

--ipv4 <ipv4>

A comma-separated list of IPv4 addresses

--ipv6 <ipv6>

A comma-separated list of IPv6 addresses

--gw4 <gw4>

Gateway IPv4 address

--gw6 <gw6>

Gateway IPv6 address

--mtu <mtu>

MTU interface value

--dhcp4

Enable DHCPv4

--no-dhcp4

Disable DHCPv4

--dhcp6

Enable DHCPv6

--no-dhcp6

Disable DHCPv6

--auto-routes-v4

Enable automatic IPv4 routes

--ignore-auto-routes-v4

Ignore automatic IPv4 routes

--auto-routes-v6

Enable automatic IPv6 routes

--ignore-auto-routes-v6

Ignore automatic IPv6 routes

--network <network>

Network ID or name

```
--node <node>
    Node ID or hostname
--iface <iface>
    Interface name
--tag <tag>
```

VLAN tag number

Example:

This command creates a task to create a VLAN with the tag 100 on the network interface eth2 on the node with the ID fd1e46de-6e17-4571-bf6b-1ac34ec1c225.

Task outcome:

```
# vinfra task show 0b978acd-367b-47ad-8572-4f4e6ffb8877
| Field | Value
 args | - fd1e46de-6e17-4571-bf6b-1ac34ec1c225
 kwargs | iface: eth2
          | tag: 100
          | backend.presentation.network.tasks.NetworkInterfaceCreateVlanTask
 name
 result | built_on: eth2
          | dhcp4: null
          | dhcp4_enabled: false
          | dhcp6: null
          | dhcp6_enabled: false
          | duplex: null
          | gw4: null
          | gw6: null
          | ignore_auto_routes_v4: true
          | ignore_auto_routes_v6: true
          | ipv4: []
          | ipv6:
          - fe80::21c:42ff:fe81:27d0/64
          | mac_addr: 00:1c:42:81:27:d0
          | mtu: 1500
          | multicast: true
          | name: eth2.100
          | node_id: fd1e46de-6e17-4571-bf6b-1ac34ec1c225
```

```
plugged: true
          roles_set: ''
          rx_bytes: 0
        | rx_dropped: 0
        | rx_errors: 0
        | rx_overruns: 0
        | rx_packets: 0
        | speeds:
          current: null
           max: null
        | state: up
        | tag: 100
        | tx_bytes: 738
        | tx_dropped: 0
        | tx_errors: 0
        | tx_overruns: 0
        | tx_packets: 7
        | type: vlan
        success
state
task_id | 0b978acd-367b-47ad-8572-4f4e6ffb8877
```

2.4.8 vinfra node network vlan delete

Delete a VLAN:

```
usage: vinfra node network vlan delete --node <node> <iface>
--node <node>
Node ID or hostname
```

<iface>

Network interface name

Example:

This command creates a task to delete the VLAN interface eth2.100 from the node with the ID fd1e46de-6e17-4571-bf6b-1ac34ec1c225.

Task outcome:

2.5 Managing Node Disks

2.5.1 vinfra node disk list

List node disks:

```
usage: vinfra node disk list (-a | --node <node>)

-a, --all
List disks on all nodes

--node <node>
Node ID or hostname to list disks on
```

Example:

This command lists disks on the node with the ID 94d58604-6f30-4339-8578-adb7903b7277. (The output is abridged to fit on page.)

2.5.2 vinfra node disk show

Show details of a disk:

```
usage: vinfra node disk show --node <node> <disk>
```

--node <node>

Node ID or hostname

<disk>

Disk ID or device name

Example:

```
# vinfra node disk show EAC7DF5D-9E60-4444-85F7-5CA5738399CC \
--node 94d58604-6f30-4339-8578-adb7903b7277
                    | Value
| Field
| being_released | False
| device
                   | sdb
| disk_status
                   | ok
| encryption
                    | EAC7DF5D-9E60-4444-85F7-5CA5738399CC
| id
| is_blink_available | False
| is_blinking
                    | False
| latency
| lun_id
 model
                    | Vz_HARDDISK2
                    | /vstorage/33aac2d5
| mountpoint
| node_id
                    94d58604-6f30-4339-8578-adb7903b7277
| role
| rpm
                   | 45589b5823ce4c188b55
| serial_number
| service_id
                    | journal_type: inner_cache
| service_params
                    | tier: 0
| service_status
                    | ok
| slot
 smart_status
                    | not_supported
space
                     | full_size: 1099511627776
                     | size: 1082101518336
                     | used: 2246164480
 tasks
                     0.0
 temperature
 transport
                    | hdd
 type
```

This commands shows the details of the disk with the ID EAC7DF5D-9E60-4444-85F7-5CA5738399CC attached to

the node with the ID 94d58604-6f30-4339-8578-adb7903b7277.

2.5.3 vinfra node disk assign

Add multiple disks to the storage cluster:

```
usage: vinfra node disk assign --disk <disk>:<role>[:<key=value,...>]
--node <node>
```

--disk <disk>:<role>[:<key=value,...>]

Disk configuration in the format:

- <disk>: disk device ID or name;
- <role>: disk role (cs, mds, journal, mds-journal, mds-system, cs-system, system);
- comma-separated key=value pairs with keys (optional):
 - tier: disk tier (0, 1, 2 or 3);
 - journal-tier: journal (cache) disk tier (0, 1, 2 or 3);
 - journal-type: journal (cache) disk type (no_cache, inner_cache or external_cache);
 - journal-disk: journal (cache) disk ID or device name;
 - journal-size: journal (cache) disk size, in bytes;
 - bind-address: bind IP address for the metadata service.

E.g., sda:cs:tier=0, journal-type=inner_cache. This option can be used multiple times.

--node <node>

Node ID or hostname

Example:

This command creates a task to assign the role cs to the disk sdc on the node with the ID f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4

Task outcome:

```
# vinfra task show 080337ba-0508-44a0-9363-eddcd9df9f0d
 Field | Value
 args
 kwargs | cluster_id: 1
          | disks:
         | - id: D3BEF4BB-AA3B-4DB6-9376-BC7CDA636700
            role: cs
             service_params: {}
           logger:
             __classname: backend.logger.tracer.TracingLogger
               prefix: POST /api/v2/1/nodes/f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4/disks/
               token: '3215629651314950'
         | node_id: f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
         | backend.tasks.disks.BulkAssignDiskTask
 name
 result | {}
 state
         success
 task_id | 080337ba-0508-44a0-9363-eddcd9df9f0d
```

2.5.4 vinfra node disk release

Release a disk from the storage cluster. Start data migration from the node as well as cluster replication and rebalancing to meet the configured redundancy level:

```
usage: vinfra node disk release [--force] --node <node> <disk>

--force
    Release without data migration

--node <node>
    Node ID or hostname

<disk>
    Disk ID or device name
```

Example:

This command creates a task to release the role cs from the disk sdc on the node with the ID

f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4.

Task outcome:

Example:

```
# vinfra task show 587a936d-3953-481c-a2cd-b1223b890bec
 Field
         | Value
 args | []
 kwargs | cluster_id: 1
          | disk_id: 43EF3400-EA95-43DE-B624-3D7ED0F9DDDD
          | force: false
          | logger:
             __classname: backend.logger.tracer.TracingLogger
             __dict:
               prefix: POST /api/v2/1/nodes/f59dabdb-
           bd1c-4944-8af2-26b8fe9ff8d4/disks/43EF3400-EA95-43DE-B624-3D7ED0F9DDDD/release/
                token: '3217122839314940'
         | node_id: f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
         | backend.tasks.disks.ReleaseDiskTask
 name
 state
         success
 task_id | 587a936d-3953-481c-a2cd-b1223b890bec
```

2.5.5 vinfra node disk blink

Start blinking the specified disk bay to identify disk for maintenance purposes:

```
usage: vinfra node disk blink on --node <node> <disk>

--node <node>
     Node ID or hostname

<disk>
     Disk ID or device name

Stop blinking the specified disk bay:
```

```
Stop blinking the specified disk bay:

usage: vinfra node disk blink off --node <node> <disk>

--node <node>

Node ID or hostname

<disk>

Disk ID or device name
```

35

```
# vinfra node disk blink on sda --node f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
```

This command starts blinking the disk sda on the node with the ID f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4.

```
# vinfra node disk blink off sda --node f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
```

This command stops blinking the disk sda on the node with the ID f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4.

2.5.6 vinfra node iscsi target add

Add an iSCSI target as a disk to a node:

```
usage: vinfra node iscsi target add [--auth-username <auth-username>]
[--auth-password <auth-password>]
--portal <portal> --node <node> <target-name>

User name

--auth-password <auth-password>
User password

User password

--portal <portal>
Portal IP address in the format IP:port (this option can be specified multiple times)

--node <node>
Node ID or hostname

<target-name>
Target name>
```

Example:

This command creates a task to connect a remote ISCSI target iqn.2014-06.com.vstorage:target1 with the IP address 172.16.24.244 and port 3260 to the node with the ID f1931be7-0a01-4977-bfef-51a392adcd94.

Task outcome:

```
# vinfra task show c42bfbe5-7292-41c2-91cb-446795535ab9
 Field | Value
 args | - f1931be7-0a01-4977-bfef-51a392adcd94
 kwargs | portals:
         | - address: 172.16.24.244
         | port: 3260
         | target_name: iqn.2014-06.com.vstorage:target1
         | backend.presentation.nodes.iscsi_initiators.tasks.ConnectTask
 result | connected: true
         | portals:
          | - address: 172.16.24.244
         | port: 3260
         | state: connected
         | target_name: iqn.2014-06.com.vstorage:target1
         success
 state
 task_id | c42bfbe5-7292-41c2-91cb-446795535ab9
```

2.5.7 vinfra node iscsi target delete

Delete an iSCSI target from a node:

```
usage: vinfra node iscsi target delete --node <node> <target-name>

--node <node>
    Node ID or hostname

<target-name>
    Target name
```

Example:

This command creates a task to disconnect a remote ISCSI target iqn.2014-06.com.vstorage:target1 from the node with the ID f1931be7-0a01-4977-bfef-51a392adcd94.

Task outcome:

2.6 vinfra cluster create

Create a storage cluster:

```
usage: vinfra cluster create [--disk <disk>:<role>[:<key=value,...>]]

[--tier-encryption {0,1,2,3}] --node <node> <cluster-name>
```

--disk <disk>:<role> [:<key=value,...>]

Disk configuration in the format:

- <disk>: disk device ID or name;
- <role>: disk role (cs, mds, journal, mds-journal, mds-system, cs-system, system);
- comma-separated key=value pairs with keys (optional):
 - tier: disk tier (0, 1, 2 or 3);
 - journal-tier: journal (cache) disk tier (0, 1, 2 or 3);
 - journal-type: journal (cache) disk type (no_cache, inner_cache or external_cache);
 - journal-disk: journal (cache) disk ID or device name;
 - journal-size: journal (cache) disk size, in bytes;
 - bind-address: bind IP address for the metadata service.

E.g., sda:cs:tier=0, journal-type=inner_cache. This option can be used multiple times.

```
--tier-encryption {0,1,2,3}
```

Enable encryption for storage cluster tiers. Encryption is disabled by default. This option can be used multiple times.

--node <node>

Node ID or hostname

<cluster-name>

Storage cluster name

Example:

This command creates a task to create the storage cluster stor1 on the node with the ID 94d58604-6f30-4339-8578-adb7903b7277. As disk roles are not explicitly specified, they are assigned automatically: mds-system to the system disk, and cs to all other disks.

Task outcome:

2.7 Showing Storage Cluster Overview and Details

2.7.1 vinfra cluster overview

Show storage cluster overview:

usage: vinfra cluster overview

```
# vinfra cluster overview
                    | Value
| Field
 chunks
                    | blocked: 0
                    | degraded: 0
                    | deleting: 0
                    | healthy: 2
                    | offline: 0
                    | overcommitted: 0
                    | pending: 0
                    | replicating: 0
                    | standby: 0
                     | total: 2
                     unique: 2
                     urgent: 0
                    | void: 0
                    | chunk_maps: 2
 fs_stat
                     | chunk_nodes: 2
                     file_maps: 2
                     | files: 9
                     inodes: 9
                     used_size: 11335680
 id
 license
                    | capacity: 1099511627776
                    | expiration_ts: null
                    | keynumber: null
                     | status: 0
                    | used_size: 11335680
 logic_space
                     free: 1099500292096
                     total: 1099511627776
                     used: 11335680
                    | stor1
 name
                    | eta: null
 repl
                     reads: 0
                     writes: 0
 resistance
                     | to_lose: 0
                     total: 1
 space_per_service | abgw: null
                    | compute: null
                     iscsi: null
                    | nfs: null
                     s3: null
 status
                    | healthy
 tiers
                    | - id: 0
                        phys_space:
                          free: 2164191700992
                          total: 2164203036672 |
```

```
| | used: 11335680 |
+-----+
```

This command shows an overview of the cluster.

2.7.2 vinfra cluster show

Show cluster details:

```
usage: vinfra cluster show
```

Example:

```
# vinfra cluster show
 Field | Value
| id
 name | stor1
 nodes | - host: stor-4.example.com.vstoragedomain
           id: 4b83a87d-9adf-472c-91f0-782c47b2d5f1
           is_installing: false
           is_releasing: false
         - host: stor-3.example.com.vstoragedomain
           id: 7d7d37b8-4c06-4f1a-b3a6-4b54257d70ce
           is_installing: false
           is_releasing: false
         - host: stor-5.example.com.vstoragedomain
           id: fd1e46de-6e17-4571-bf6b-1ac34ec1c225
           is_installing: false
           is_releasing: false
         - host: stor-1.example.com.vstoragedomain
           id: 94d58604-6f30-4339-8578-adb7903b7277
           is_installing: false
           is_releasing: false
         - host: stor-2.example.com.vstoragedomain
            id: f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
           is_installing: false
            is_releasing: false
```

This command shows cluster details.

2.8 vinfra cluster delete

Delete the storage cluster:

```
usage: vinfra cluster delete
```

Example:

```
# vinfra cluster delete
Operation waiting (timeout=600s) [Elapsed Time: 0:01:09] ... |
Operation successful
```

This command releases all nodes from the storage cluster.

CHAPTER 3

Managing Compute Cluster

3.1 vinfra service compute cluster create

Create a compute cluster:

--public-network <network>

A physical network to connect the public virtual network to. It must include the 'VM public' traffic type.

```
--subnet cidr=CIDR[,key=value,...]
```

Subnet for IP address management in the public virtual network (the --public-network option is required):

- · cidr: subnet range in CIDR notation;
- comma-separated key=value pairs with keys (optional):
 - gateway: gateway IP address;
 - dhcp: enable/disable the virtual DHCP server;
 - allocation-pool: allocation pool of IP addresses from CIDR in the format ip1-ip2, where ip1 and ip2 are starting and ending IP addresses correspondingly. Specify the key multiple times to create multiple IP pools;
 - dns-server: DNS server IP address, specify multiple times to set multiple DNS servers.

Example: --subnet cidr=192.168.5.0/24, dhcp=enable.

```
--cpu-model <cpu-model>
```

CPU model for virtual machines.

--force

Skip checks for minimal hardware requirements.

--nodes <nodes>

A comma-separated list of node IDs or hostnames.

Example:

This command creates a task to create the compute cluster from five nodes specified by ID. It also specifies the virtual IP address (must belong to the network with the Compute API traffic type), the public network for VMs, the gateway, the allocation pool of IP addresses to assign to VMs, and the DNS servers to use.

Task outcome:

```
# vinfra task show be517afa-fae0-457e-819c-f4d6399f3ae2
 Field
           | Value
           | - admin
 args
           | enable_nested: true
 kwargs
           | external_network:
              roles_set_id: dd42723e-1318-4f8f-9a43-b303ab09cbbe
              subnet:
                allocation_pools:
                 - end_address: 10.94.129.79
                  start_address: 10.94.129.64
                cidr: 10.94.0.0/16
                dns_servers:
                 - 10.30.0.27
                 - 10.30.0.28
                enable_dhcp: true
                gateway: 10.94.0.1
```

```
| nodes:
| 7ffa9540-5a20-41d1-b203-e3f349d62565
| 02ff64ae-5800-4090-b958-18b1fe8f5060
| 6e8afc28-7f71-4848-bdbe-7c5de64c5013
| 37c70bfb-c289-4794-8be4-b7a40c2b6d95
| 827a1f4e-56e5-404f-9113-88748c18f0c2
| name | backend.presentation.compute.tasks.DeployComputeClusterTask | progress | 100
| state | success | task_id | be517afa-fae0-457e-819c-f4d6399f3ae2
```

3.2 Showing Compute Cluster Details and Overview

3.2.1 vinfra service compute cluster show

Display compute cluster details:

```
usage: vinfra service compute cluster show
```

```
# vinfra service compute cluster show
 Field
               | Value
 capabilities | cpu_models:
               | - SandyBridge
               | - IvyBridge
               | - Haswell
               | - Haswell-noTSX
               - Broadwell
               - Broadwell-noTSX
               - Skylake-Client
               | - Skylake-Server
                - HostPassthrough
               | os_distributions:
                  linux:
                     centos6: Centos 6
                     centos7: Centos 7
                     debian9: Debian 9 (Stretch)
                     linux: Generic Linux
                     rhel7: Red Hat Enterprise Linux
                     ubuntu16.04: Ubuntu 16.04 LTS
                     ubuntu18.04: Ubuntu 18.04 LTS
```

This command shows the status and capabilities of the compute cluster.

3.2.2 vinfra service compute cluster stat

Display compute cluster statistics:

```
usage: vinfra service compute cluster stat
```

```
# vinfra service compute cluster stat
 Field
          | Value
 compute | block_capacity: 0
           | block_usage: 0
           | cpu_usage: 0.0
            mem_total: 0
            mem_usage: 0
           | vcpus: 0
 datetime | 2018-09-11T15:50:18.758258
 physical | block_capacity: 1099511627776
            block_free: 1099498911464
           cpu_cores: 10
           | mem_total: 41006247936
 reserved | cpus: 5
           | memory: 17721982976
 servers | count: 0
            error: 0
            in_progress: 0
            running: 0
            stopped: 0
            top:
              disk: []
              memory: []
              vcpus: []
```

+-----+

This command shows the overview of the compute cluster.

3.3 vinfra service compute cluster set

Change compute cluster parameters:

vinfra service compute cluster set [--cpu-model <cpu-model>]

--cpu-model <cpu-model>

Set the default CPU model for virtual machines (SandyBridge, IvyBridge, Haswell, Haswell-noTSX, Broadwell, Broadwell-noTSX, Skylake-Client, Skylake-Server, HostPassthrough)

Example:

vinfra service compute cluster set --cpu-model Haswell

This command sets the default CPU model for VMs to Haswell.

3.4 Managing Compute Nodes

3.4.1 vinfra service compute node add

Add a node to the compute cluster:

usage: vinfra service compute node add [--compute] [--controller] [--force] <node-id>

--compute

Compute node role

--controller

Compute controller node role

--force

Skip checks for minimal hardware requirements

<node-id>

ID or hostname of the compute node

This command creates a task to add the node with the ID 827a1f4e-56e5-404f-9113-88748c18f0c2 to the compute cluster.

Task outcome:

3.4.2 vinfra service compute node list

List compute nodes:

```
usage: vinfra service compute node list
```

Example:

This command lists nodes in the compute cluster.

3.4.3 Showing Compute Node Details

Display compute node details:

```
usage: vinfra service compute node show <node>
```

<node>

Node ID or hostname

Example:

```
# vinfra service compute node show 7ffa9540-5a20-41d1-b203-e3f349d62565
 Field
                      | Value
| host_ip
                      | 10.37.130.101
 hypervisor_hostname | stor-1.example.com.vstoragedomain
 hypervisor_id
                      | 7ffa9540-5a20-41d1-b203-e3f349d62565
| id
 state
 statistics
                      | compute:
                        block_capacity: 0
                         block_usage: 0
                      | cpu_usage: 0
                      | mem_total: 0
                         mem_usage: 0
                         vcpus: 0
                      | datetime: '2018-09-11T16:39:15.290999+<u>00:00</u>'
                       physical:
                         cpu_cores: 2
                         mem_free: 414105600
                         mem_total: 8201244672
                       reserved:
                         cpus: 1
                         memory: 5773
                      10
```

This command shows the details of the compute node with the ID 7ffa9540-5a20-41d1-b203-e3f349d62565.

3.4.4 vinfra service compute node fence

Fence a compute node:

```
usage: vinfra service compute node fence <node>
```

<node>

Node ID or hostname

Example:

```
# vinfra service compute node fence e6255aed-d6e7-41b2-ba90-86164c1cd9a6
Operation successful
```

This command fences the node with the ID e6255aed-d6e7-41b2-ba90-86164c1cd9a6.

3.4.5 vinfra service compute node unfence

Unfence a compute node:

```
usage: vinfra service compute node unfence <node>
```

<node>

Node ID or hostname

Example:

```
# vinfra service compute node unfence e6255aed-d6e7-41b2-ba90-86164c1cd9a6
Operation successful
```

This command unfences the node with the ID e6255aed-d6e7-41b2-ba90-86164c1cd9a6.

3.4.6 vinfra service compute node release

Release a node from the compute cluster:

ID or hostname of the compute node

```
# vinfra service compute node release --node 827a1f4e-56e5-404f-9113-88748c18f0c2
+------+
| Field | Value
+-----+
```

```
| task_id | 3b39738c-80a6-40a6-a50d-c3c8118ed212 |
+-----+
```

This command creates a task to release the node with the ID 827a1f4e-56e5-404f-9113-88748c18f0c2 from the compute cluster.

Task outcome:

3.5 Managing Networks

3.5.1 vinfra service compute network create

Create a compute network:

--dhcp

Enable DHCP

--no-dhcp

Disable DHCP

--dns-nameserver <dns-nameserver>

DNS server IP address. This option can be used multiple times.

--allocation-pool <allocation-pool>

Allocation pool to create inside the network in the format: ip_addr_start-ip_addr_end. This option can

be used multiple times.

--gateway <gateway>

Gateway IP address

--no-gateway

Do not configure a gateway for this network

--ip-version <ip-version>

Network IP version

--type {vxlan|flat}

Virtual network type (vxlan is private and flat is public)

--physical-network <physical-network>

A physical network to link to a flat network

--cidr <cidr>

Subnet range in CIDR notation

<network-name>

Network name

Example:

```
# vinfra service compute network create myprivnet --type vxlan \
--cidr 192.128.128.0/24 --gateway 192.128.128.1
| Field
                 | Value
                  | 3848fb5d-bc98-4320-acd0-cde2df7c5bdd
| id
                | myprivnet
 physical_network |
| project_id
                   | 72a5db3a033c403a86756021e601ef34
                   | allocation_pools:
 subnet
                   | - end: 192.128.128.254
                      start: 192.128.128.2
                   | cidr: 192.128.128.0/24
                   | dns_nameservers: []
                   | enable_dhcp: true
                    gateway_ip: 192.128.128.1
                   ip_version: 4
 type
                    vxlan
```

This command creates a private network myprivnet with the specific CIDR and gateway.

3.5.2 vinfra service compute network list

List compute networks:

```
usage: vinfra service compute network list
```

Example:

This command lists networks used in the compute cluster. (The output is abridged to fit on page.)

3.5.3 vinfra service compute network show

Display compute network details:

```
usage: vinfra service compute network show <network>
```

<network>

Network ID or name



```
| flat
type
```

This command shows the details of the network with the ID 417606ac-1dbe-426a-844d-e047831ddce9.

3.5.4 vinfra service compute network set

vinfra service compute network set myprivnet --no-dhcp

Modify compute network parameters:

```
usage: vinfra service compute network set [--dhcp | --no-dhcp]
                                             [--dns-nameserver <dns-nameserver>]
                                             [--allocation-pool <allocation-pool>]
                                             [--gateway <gateway> | --no-gateway]
                                             [--name <name>] <network>
--dhcp
     Enable DHCP
--no-dhcp
     Disable DHCP
--dns-nameserver <dns-nameserver>
     DNS server IP address. This option can be used multiple times.
--allocation-pool <allocation-pool>
     Allocation pool to create inside the network in the format: ip_addr_start-ip_addr_end. This option can
     be used multiple times.
--gateway <gateway>
     Gateway IP address
--no-gateway
     Do not configure a gateway for this network
--name <name>
     A new name for the network
<network>
     Network ID or name
Example:
```

```
Field
                  | Value
id
                   3848fb5d-bc98-4320-acd0-cde2df7c5bdd
                   myprivnet
name
physical_network
                   72a5db3a033c403a86756021e601ef34
project_id
subnet
                   allocation_pools:
                   - end: 192.128.128.254
                     start: 192.128.128.2
                   cidr: 192.128.128.0/24
                   dns_nameservers: []
                   enable_dhcp: false
                   gateway_ip: 192.128.128.1
                   ip_version: 4
                   vxlan
type
```

This command disables DHCP for the private network myprivnet.

3.5.5 vinfra service compute network delete

Delete a compute network:

```
usage: vinfra service compute network delete <network>
```

<network>

Network ID or name

Example:

```
# vinfra service compute network delete myprivnet
Operation successful
```

This command deletes the private network myprivnet.

3.6 Managing Images

3.6.1 vinfra service compute image create

Create a new compute image:

```
usage: vinfra service compute image create [--min-disk <size-gb>] [--min-ram <size-mb>]
[--os-distro <os-distro>] [--protected]
[--disk-format <disk_format>]
```

```
[--container-format <format>]
                                                --file <file> <image-name>
--min-disk <size-gb>
      Minimum disk size required to boot from image, in gigabytes
--min-ram <size-mb>
      Minimum RAM size required to boot from image, in megabytes
--os-distro <os-distro>
      OS distribution. To list available distributions, run service compute cluster show.
--protected
      Protect image from deletion
--disk-format <disk_format>
      Disk format aki, ami, ari, detect, iso, ploop, qcow2, raw, vdi, vhd, vhdx, vmdk (default: detect)
--container-format <format>
      Container format: aki, ami, ari, bare, docker, ovf, ova (default: bare)
--file <file>
      Create image from a local file
<image-name>
```

Example:

Image name

This command creates a task to create a Cirros image from the local file and upload it to Acronis Software-Defined Infrastructure.

Task outcome:

```
# vinfra task show 03874663-d03f-4891-a10b-64837e7faf43
+------+
| Field | Value
+-----+
```

3.6.2 vinfra service compute image list

List compute images:

```
usage: vinfra service compute image list
```

Example:

This command lists images available to the compute cluster.

3.6.3 vinfra service compute image show

Display compute image details:

```
usage: vinfra service compute image show <image>
```

<image>

Image ID or name

```
min_disk
                 10
min_ram
name
                 | cirros
os_distro
                   linux
                 | linux
os_type
project_id
                 | 72a5db3a033c403a86756021e601ef34
protected
                 | False
size
                  | 12716032
status
                 | active
tags
updated_at
                  2018-09-11T13:29:13Z
virtual_size
visibility
                  public
```

This command shows the details of the default Cirros image.

3.6.4 vinfra service compute image set

Modify compute image parameters:

```
usage: vinfra service compute image set [--min-disk <size-gb>] [--min-ram <size-mb>]
                                           [--os-distro <os-distro>] [--protected]
                                           [--name <name>] <image>
--min-disk <size-gb>
     Minimum disk size required to boot from image, in gigabytes
--min-ram <size-mb>
     Minimum RAM size required to boot from image, in megabytes
--os-distro <os-distro>
     OS distribution. To list available distributions, run service compute cluster show.
--protected
     Protect image from deletion
--name <name>
     Image name
<image>
     Image ID or name
Example:
```

```
# vinfra service compute image set 4741274f-5cca-4205-8f66-a2e89fb346cc --protected --min-ram 1
| Field
                 | Value
 checksum | 443b7623e27ecf03dc9e01ee93f67afe
 container_format | bare
 created_at | 2018-09-11T13:29:10Z
 disk_format
                 | qcow2
 file
                  | /api/v2/compute/images/4741274f-5cca-4205-8f66-a2e89fb346cc/file/
                  | 4741274f-5cca-4205-8f66-a2e89fb346cc
 id
 min_disk
 min_ram
 name
                  | cirros
                 | linux
| os_distro
 os_type
                  | linux
| project_id
                  | 72a5db3a033c403a86756021e601ef34
 protected
                 12716032
 size
 status
                  | active
                  | []
 tags
 updated_at
                  | 2018-09-12T09:26:29Z
 virtual_size
 visibility
                  | public
```

This command protects the default Cirros image and sets the minimum RAM size for it to 1 GB.

3.6.5 vinfra service compute image save

Download a compute image:

```
usage: vinfra service compute image save [--file <filename>] <image>

--file <filename>
    File to save the image to (default: stdout)

<image>
    Image ID or name
```

Example:

```
# vinfra service compute image save 4741274f-5cca-4205-8f66-a2e89fb346cc --file cirros.qcow2
Operation successful
```

This command downloads the default Cirros image to the local disk as cirros.qcow2.

3.6.6 vinfra service compute image delete

Delete a compute image:

```
usage: vinfra service compute image delete <image>
```

<image>

Image ID or name

Example:

```
\# vinfra service compute image delete 179f45ef-c5d6-4270-b0c0-085b542544c5 Operation successful
```

This command deletes the image with the ID 179f45ef-c5d6-4270-b0c0-085b542544c5.

3.7 Managing Flavors

3.7.1 vinfra service compute flavor create

Create a new compute flavor:

Example:

Flavor name

```
# vinfra service compute flavor create myflavor --vcpus 1 --ram 3072
+-----+
| Field | Value
+-----+
```

This command creates a flavor myflavor with 1 vCPU and 3 GB RAM.

3.7.2 vinfra service compute flavor list

List compute flavors:

```
usage: vinfra service compute flavor list
```

Example:

# vinfra service compute flavor list	+		.	+
id	 name +	ram	swap	vcpus
100	+ tiny	 512		 1
101	small	2048	0	1
102	medium	4096	0	2
103	large	8192	0	4
104	xlarge	16384	0	8
561a48ea-0c1c-4152-8b7d-e4b4af276c2d	myflavor	3072	0	1
+	+	+	+	+

This command lists all flavors.

3.7.3 vinfra service compute flavor show

Display compute flavor details:

```
usage: vinfra service compute flavor show <flavor>
```

<flavor>

Flavor ID or name

```
# vinfra service compute flavor show myflavor
+-----+
| Field | Value
+-----+
```

This command shows the details of the flavor myflavor.

3.7.4 vinfra service compute flavor delete

Delete a compute flavor:

```
usage: vinfra service compute flavor delete <flavor>
```

<flavor>

Flavor ID or name

Example:

```
# vinfra service compute flavor delete myflavor
Operation successful
```

This command deletes the flavor myflavor.

3.8 Managing Storage Policies

You can manage storage policies only after creating the compute cluster.

3.8.1 vinfra cluster storage-policy create

Create a new storage policy:

```
usage: vinfra cluster storage-policy create --tier {0,1,2,3}
(--replicas <norm>[:<min>] |
--encoding <M>+<N>) --failure-domain
{disk,host,rack,row,room} <name>
```

```
--tier {0,1,2,3}
Storage tier
```

```
--replicas <norm>[:<min>]
```

Storage replication mapping in the format:

- norm: the number of replicas to maintain;
- min: the minimum required number of replicas (optional).

--encoding <M>+<N>

Storage erasure encoding mapping in the format:

- M: the number of data blocks;
- N: the number of parity blocks.

```
--failure-domain {disk,host,rack,row,room}
Storage failure domain
```

<name>

Storage policy name

Example:

This command creates a storage policy mystorpolicy with the tier set to 3, redundancy scheme to erasure coding 3+2, and failure domain set to host.

3.8.2 vinfra cluster storage-policy list

List existing storage policies:

```
usage: vinfra cluster storage-policy list
```

```
# vinfra cluster storage-policy list
```

This command lists storage policies available to the compute cluster.

3.8.3 vinfra cluster storage-policy show

Show details of a storage policy:

```
usage: vinfra cluster storage-policy show <storage-policy>
```

<storage-policy>

Storage policy ID or name

Example:

This command shows the details of the storage policy mystorpolicy.

3.8.4 vinfra cluster storage-policy set

Modify storage policy parameters:

--name <name>

A new name for the storage policy

```
--tier {0,1,2,3}
Storage tier
```

--replicas <norm>[:<min>]

Storage replication mapping in the format:

- norm: the number of replicas to maintain;
- min: the minimum required number of replicas (optional).

```
--encoding <M>+<N>
```

Storage erasure encoding mapping in the format:

- M: the number of data blocks;
- N: the number of parity blocks.

```
--failure-domain {disk,host,rack,row,room}
Storage failure domain
```

<storage-policy>

Storage policy ID or name

Example:

This command changes the redundancy type for the storage policy mystorpolicy from erasure coding 3+2 to 5+2.

3.8.5 vinfra cluster storage-policy delete

The default policy cannot be deleted.

Remove an existing storage policy:

```
usage: vinfra cluster storage-policy delete <storage-policy>
```

<storage-policy>

Storage policy ID or name

Example:

```
# vinfra cluster storage-policy delete mystorpolicy
Operation successful
```

This command deletes the storage policy mystorpolicy.

3.9 Managing Volumes

3.9.1 vinfra service compute volume create

Create a new compute volume:

--description <description>

Volume description

--network-install <network_install>

Perform network install (true or false)

--image <image>

Source compute image ID or name

--storage-policy <storage_policy>

Storage policy ID or name

--size <size-gb>

Volume size, in gigabytes

<volume-name>

Volume name

```
# vinfra service compute volume create myvolume --storage-policy default --size 8
                               | Value
| Field
| attachments
| availability_zone
                               | False
| bootable
consistencygroup_id
                              | 2018-09-12T12:30:12.665916
| created_at
| description
                                | False
| encrypted
                                | c9c0e9e7-ce7a-4566-99d5-d7e40f2987ab
| id
| imageRef
| migration_status
| multiattach
                                | False
                                | myvolume
| name
| network_install
                                | False
| os-vol-host-attr:host
| os-vol-mig-status-attr:migstat |
| os-vol-mig-status-attr:name_id |
| project_id
                                | 72a5db3a033c403a86756021e601ef34
| replication_status
                                | 8
| size
| snapshot_id
| source_volid
                                | creating
| storage_policy_name
                                | default
| updated_at
| user_id
                               | 98bf389983c24c07af9677b931783143
| volume_image_metadata
```

This command creates a volume myvolume sized 8 GB and chooses the default storage policy for it.

3.9.2 vinfra service compute volume list

List compute volumes:

```
usage: vinfra service compute volume list
```

Example:

This command lists volumes available to the compute cluster. (The output is abridged to fit on page.)

3.9.3 vinfra service compute volume show

Display compute volume details:

```
usage: vinfra service compute volume show <volume>
```

<volume>

Volume ID or name

Example:

# vinfra service compute volume show myvolume			
Field	++ Value		
+	+		
attachments			
availability_zone	nova		
bootable	False		
consistencygroup_id			
created_at	2018-09-12T12:30:12.665916		
description	l l		
encrypted	False		
id	c9c0e9e7-ce7a-4566-99d5-d7e40f2987ab		
imageRef			
migration_status	l l		
multiattach	False		
name	myvolume		
network_install	False		
os-vol-host-attr:host	stor-1.example.com.vstoragedomain@vstorage#vstorage		
os-vol-mig-status-attr:migstat	l I		
os-vol-mig-status-attr:name_id			
project_id	72a5db3a033c403a86756021e601ef34		
replication_status	l l		
size	8		
snapshot_id	l I		
source_volid			
status	available		
storage_policy_name	default		
updated_at	2018-09-12T12:30:33.167654		
user_id	98bf389983c24c07af9677b931783143 		
volume_image_metadata			
· 	 		

This command shows the details for the volume myvolume.

3.9.4 vinfra service compute volume set

Modify volume parameters:

--description <description>

Volume description

--network-install <network_install>

Perform network install (true or false)

--storage-policy <storage_policy>

Storage policy ID or name

--bootable <bootable>

Make bootable (true or false)

--name <name>

A new name for the volume

<volume>

Volume ID or name

Field	Value	1
attachments	[]	
availability_zone	nova	1.3
bootable	False	1.
consistencygroup_id		1
created_at	2018-09-12T12:30:12.665916	1
description		1
encrypted	False	1
id	c9c0e9e7-ce7a-4566-99d5-d7e40f2987ab	1
imageRef		1.3
migration_status		
multiattach	False	1.
name	myvolume	1.1
network_install	False	

```
os-vol-host-attr:host
                                stor-1.example.com.vstoragedomain@vstorage#vstorage
os-vol-mig-status-attr:migstat
os-vol-mig-status-attr:name_id |
                                 72a5db3a033c403a86756021e601ef34
project_id
replication_status
size
snapshot_id
source_volid
                                 available
storage_policy_name
                                 mystorpolicy
updated_at
                                 2018-09-12T12:55:29.298717
                                 98bf389983c24c07af9677b931783143
user_id
volume_image_metadata
```

This command changes the storage policy of the volume myvolume to mystorpolicy.

3.9.5 vinfra service compute volume extend

Extend a compute volume:

```
usage: vinfra service compute volume extend --size <size_gb> <volume>
```

<volume>

Volume ID or name

Example:

```
# vinfra service compute volume extend myvolume --size 16
Operation successful
```

This command extends the volume myvolume to 16 GB.

3.9.6 vinfra service compute server volume attach

Attach a volume to a compute server:

```
usage: vinfra service compute server volume attach --server <server> <volume>
```

--server <server>

Compute server ID or name

<volume>

Volume ID or name

Example:

This command attaches the available volume with the ID e4cb5363-1fb2-41f5-b24b-18f98a388cba to the VM with the ID 871fef54-519b-4111-b18d-d2039e2410a8.

3.9.7 vinfra service compute server volume detach

Detach a volume from a compute server:

```
usage: vinfra service compute server volume detach --server <server> <volume>

--server <server>
    Compute server ID or name

<volume>
    Volume ID or name
```

Example:

```
# vinfra service compute server volume detach e4cb5363-1fb2-41f5-b24b-18f98a388cba \
--server 871fef54-519b-4111-b18d-d2039e2410a8
Operation successful
```

This command detaches the volume with the ID e4cb5363-1fb2-41f5-b24b-18f98a388cba from the VM with the ID 871fef54-519b-4111-b18d-d2039e2410a8.

3.9.8 vinfra service compute volume delete

Delete a compute volume:

```
usage: vinfra service compute volume delete <volume>
```

<volume>

Volume ID or name

Example:

```
# vinfra service compute volume delete myvolume2
Operation successful
```

This command deletes the volume myvolume2.

3.10 Managing Virtual Machines

3.10.1 vinfra service compute server create

Create a new compute server:

--metadata <metadata>

Server metadata

--user-data <user-data>

User data file

--key-name <key-name>

Key pair to inject

--config-drive

Use an ephemeral drive

--count <count>

If count is specified and greater than 1, the name argument is treated as a naming pattern.

--network <id=id[,key=value,...]>

Create a compute server with a specified network. Specify this option multiple times to create multiple networks.

- id: attach network interface to a specified network (ID or name);
- comma-separated key=value pairs with keys (optional):
 - mac: MAC address for network interface;
 - fixed-ip: fixed IP address for network interface;
 - spoofing-protection: enable or disable spoofing protection for network interface (on or off).

```
--volume <source=source[,key=value,...]>
```

Create a compute server with a specified volume. Specify this option multiple times to create multiple volumes.

- source: Source type (volume, image, snapshot, or blank);
- comma-separated key=value pairs with keys (optional):
 - id: resource ID or name for the specified source type (required for source types volume, image, and snapshot);
 - size: block device size, in gigabytes (required for source types image and blank);
 - boot-index: block device boot index (required for multiple volumes with source type volume);
 - bus: block device controller type (ide, usb, virtio, scsi, or sata);
 - type: block device type (disk or cdrom);
 - rm: remove block device on compute server termination (yes or no);
 - storage-policy: block device storage policy.

--flavor <flavor>

Flavor ID or name

<server-name>

A new name for the compute server

```
created
            | 2018-09-12T13:25:02Z
description |
flavor
            | 100
host
            | f6656fb5-e165-4afa-a119-45882acc6af1
id
key_name
metadata
            | {}
name
            | myvm
networks
            power_state | NOSTATE
project_id | 72a5db3a033c403a86756021e601ef34
            | BUILD
status
task_state | scheduling
updated | 2018-09-12T13:25:03Z
user_data
volumes
            | []
```

This command creates a virtual machine 'myvm based on the default Cirros image and the flavor tiny and connects it to the network private with the fixed IP address 192.168.128.100.

3.10.2 vinfra service compute server list

List compute servers:

```
usage: vinfra service compute server list
```

Example:

This command lists all virtual machines in the compute cluster.

3.10.3 vinfra service compute server show

Display compute server details:

```
usage: vinfra service compute server show <server>
```

<server>

Compute server ID or name

Example:

```
# vinfra service compute server show myvm
| Field
           | Value
| config_drive |
| description |
| flavor | 100
host
            | stor-4.example.com.vstoragedomain
id
           | 8cd29296-8bee-4efb-828d-0e522d816c6e
 key_name
 metadata
            | {}
name
            | myvm
            | - id: 1bf2c9da-e324-49f0-8d41-20410615f905
 networks
               ipam_enabled: true
               ips:
             | - 192.168.128.100
              mac_addr: fa:16:3e:54:04:f0
               name: private
               spoofing_protection: false
 power_state | RUNNING
project_id | 72a5db3a033c403a86756021e601ef34
status | ACTIVE
| task_state |
updated | 2018-09-12T13:30:53Z
 user_data |
           | - 30092d44-3bdd-46d8-a360-a5bc6434cbf8
```

This command shows the details of the virtual machine myvm.

3.10.4 vinfra service compute server stat

Display compute server statistics:

```
usage: vinfra service compute server stat <server>
```

<server>

Compute server ID or name

```
# vinfra service compute server stat myvm
+-----+
| Field | Value |
+-----+
| datetime | 2018-09-12T13:37:46.803999+00:00 |
```

This command shows the statistics for the virtual machine myvm.

3.10.5 vinfra service compute server iface attach

Attach a network to a compute server:

Example:

This command attaches the private network myprivnet to the virtual machine myvm.

3.10.6 vinfra service compute server iface list

List compute server networks:

```
usage: vinfra service compute server iface list --server <server>
```

--server <server>

Compute server ID or name

Example:

This command lists the virtual networks that the virtual machine myvm is attached to. It also shows VM's IP address in each network.

3.10.7 vinfra service compute server iface detach

Detach a network interface from a compute server:

```
usage: vinfra service compute server iface detach --server <server> <interface>
```

--server <server>

Compute server ID or name

<interface>

Network interface ID

Example:

```
# vinfra service compute server iface detach 471e37fd-13ae-4b8f-b70c-90ac02cc4386 \
--server 6c80b07f-da46-4a8a-89a4-eecb8faceb27
Operation successful
```

This command detaches the network interface with the ID 471e37fd-13ae-4b8f-b70c-90ac02cc4386 from the VM with the ID 6c80b07f-da46-4a8a-89a4-eecb8faceb27.

3.10.8 vinfra service compute server log

Display compute server log:

usage: vinfra service compute server log <server>

<server>

Compute server ID or name

Example:

vinfra service compute server log myvm > myvm.log

This command prints the log of the virtual machine myvm to the file myvm.log.

3.10.9 vinfra service compute server migrate

Migrate a compute server to another host:

usage: vinfra service compute server migrate [--cold] [--node <node>] <server>

--cold

Perform cold migration. If not set, try to determine migration type automatically.

--node <node>

Destination node ID or hostname

<server>

Compute server ID or name

Example:

vinfra service compute server migrate 6c80b07f-da46-4a8a-89a4-eecb8faceb27 \ --node e6255aed-d6e7-41b2-ba90-86164c1cd9a6 Operation successful

This command starts migration of the VM with the ID 6c80b07f-da46-4a8a-89a4-eecb8faceb27 to the compute node with the ID e6255aed-d6e7-41b2-ba90-86164c1cd9a6.

3.10.10 vinfra service compute server resize

Resize a compute server:

usage: vinfra service compute server resize --flavor <flavor> <server>

--flavor <flavor>

Apply flavor with ID or name

<server>

Compute server ID or name

Example:

vinfra service compute server resize myvm --flavor small
Operation successful

This command changes the flavor of the virtual machine myvm to small.

3.10.11 vinfra service compute server start

Start a compute server:

usage: vinfra service compute server start <server>

<server>

Compute server ID or name

Example:

vinfra service compute server start myvm
Operation successful

This command starts the virtual machine myvm.

3.10.12 vinfra service compute server pause

Pause a compute server:

usage: vinfra service compute server pause <server>

<server>

Compute server ID or name

Example:

vinfra service compute server pause myvm

This command pauses the running virtual machine myvm.

3.10.13 vinfra service compute server unpause

Unpause a compute server:

usage: vinfra service compute server unpause <server>

<server>

Compute server ID or name

Example:

vinfra service compute server unpause myvm

This command unpauses the paused virtual machine myvm.

3.10.14 vinfra service compute server suspend

Suspend a compute server:

usage: vinfra service compute server suspend <server>

<server>

Compute server ID or name

Example:

vinfra service compute server suspend myvm
Operation successful

This command suspends the running virtual machine myvm.

3.10.15 vinfra service compute server resume

Resume a compute server:

usage: vinfra service compute server resume <server>

<server>

Compute server ID or name

Example:

vinfra service compute server resume myvm
Operation successful

This command resumes the suspended virtual machine myvm.

3.10.16 vinfra service compute server reboot

Reboot a compute server:

usage: vinfra service compute server reboot [--hard] <server>

--hard

Perform hard reboot

<server>

Compute server ID or name

Example:

vinfra service compute server reboot myvm
Operation successful

This command reboots the virtual machine myvm.

3.10.17 vinfra service compute server reset-state

Reset compute server state:

usage: vinfra service compute server reset-state [--state-error] <server>

--state-error

Reset server to 'ERROR' state

<server>

Compute server ID or name

Example:

vinfra service compute server reset-state myvm
Operation successful

This command resets the state of the virtual machine myvm.

3.10.18 vinfra service compute server stop

Shut down a compute server:

usage: vinfra service compute server stop [--hard] <server>

--hard

Power off a compute server

<server>

Compute server ID or name

Example:

vinfra service compute server stop myvm
Operation successful

This command stops the virtual machine myvm.

3.10.19 vinfra service compute server evacuate

Evacuate a stopped compute server from a failed host:

usage: vinfra service compute server evacuate <server>

<server>

Compute server ID or name

Example:

vinfra service compute server evacuate ``myvm``
Operation successful

This command evacuates the stopped VM myvm from its node to another, healthy compute node.

3.10.20 vinfra service compute server delete

Delete a compute server:

```
usage: vinfra service compute server delete <server>
```

<server>

Compute server ID or name

Example:

```
# vinfra service compute server delete myvm
Operation successful
```

This command deletes the virtual machine myvm.

3.11 vinfra service compute cluster delete

Delete all nodes from the compute cluster:

```
usage: vinfra service compute cluster delete
```

Example:

```
# vinfra service compute cluster delete

+-----+

| Field | Value |

+-----+

| task_id | 063e8a15-fcfe-4629-865f-b5e5fa44b38f |

+------+
```

This command creates a task to release nodes from the compute cluster.

Task outcome:

CHAPTER 4

Managing General Settings

4.1 Managing Licenses

4.1.1 vinfra cluster license load

Load a license from a key.

```
usage: vinfra cluster license load --key <license-key> --type <license-type>

--key <license-key>
    License key to register. Specify this option multiple times to register multiple keys.

--type <license-type>
    License type (prolong or upgrade)
```

Example:

This command install the license from the key A38600-3P6W74-RZSK58-Y9ZH05-2X7J48.

4.1.2 vinfra cluster license show

Show details of the installed license:

```
usage: vinfra cluster license show
```

Example:

This command shows the details of the currently installed license.

4.2 Managing Users

4.2.1 vinfra cluster user list-available-roles

List available user roles:

```
usage: vinfra cluster user list-available-roles
```

```
# vinfra cluster user list-available-roles
                                                                     | id
| Can create cluster, join nodes to cluster, and manage (assign and | cluster | Cluster
| release) disks.
| Can add and remove SSH keys for cluster nodes access.
                                                                       ssh
| Viewer role (read only)
                                                                               | Viewer
                                                                     | viewer
| Can create and manage compute cluster.
                                                                     | compute | Compute
| Can modify network settings and roles.
                                                                       network | Network
| Can install updates.
                                                                      updates | Updates
| Can perform all management operations.
                                                                     | admin | Administrator |
```

```
| Can create and manage S3 cluster. | s3 | S3 | Can create and manage Acronis Backup Gateway. | abgw | ABGW | Can create and manage iSCSI targets LUNs and CHAP users. | iscsi | iSCSI | Can create and manage NFS. | nfs | NFS | Can create and manage NFS. | can create and manage
```

This command lists user roles available in Acronis Software-Defined Infrastructure.

4.2.2 vinfra cluster user create

Add an admin panel user:

```
# vinfra cluster user create user1 --roles viewer --enable \
--description "A guest user"
Password:
| Field
                     | Value
| description
                     | A guest user
| external_id
| external_provider |
| id
                     | 538e54fdeb13498e8f0bbff6773de5a1
| is_enabled
                     | True
                     | False
| is_group
 is_superuser
                     | False
 name
                     | user1
```

This command creates and enables the user user1, assigns it the role Viewer, and sets its password and description.

4.2.3 vinfra cluster user list

List all admin panel users:

```
usage: vinfra cluster user list
```

Example:

# vinfra cluster user list				.
id	name	is_enabled 	is_superuser	roles
60b67333c545442f98c084a56db7a06d	admin	True	True	! !
+		t		++

This command lists users registered in Acronis Software-Defined Infrastructure.

4.2.4 vinfra cluster user show

Show details of an admin panel user:

```
usage: vinfra cluster user show <user>
```

<user>

User ID or name

is_group	False		
	True		
is_superuser			
name	admin		
roles	1		
+	+	+	

This command shows the details of the user admin.

4.2.5 vinfra cluster user set

Modify admin panel user parameters:

```
usage: vinfra cluster user set [--description <description>] [--enable | --disable]
                                  [--set-roles <roles> | --add-roles <roles> |
                                  --del-roles <roles>] [--password] [--name <name>] <user>
--description <description>
     User description
--enable
     Enable user
--disable
     Disable user
--set-roles <roles>
     A comma-separated list of user roles to set (overwrites the current user roles)
--add-roles <roles>
     A comma-separated list of user roles to add
--del-roles <roles>
     A comma separated list of user roles to remove
--password
     User password
--name <name>
     A new name for the user
<user>
     User ID or name
Example:
```

This command adds a description for the user admin.

4.2.6 vinfra cluster user change-password

Change password of an admin panel user:

```
usage: vinfra cluster user change-password
```

Example:

```
# vinfra cluster user change-password
Current password:
New password:
Confirm password:
```

This command changes the password of the current user.

4.2.7 vinfra cluster user delete

Remove an admin panel user:

```
usage: vinfra cluster user delete <user>
```

<user>

User ID or name

```
# vinfra cluster user delete user1
Operation successful
```

This command deletes the user user1.

4.3 Managing SSH Keys

4.3.1 vinfra cluster sshkey add

Add an SSH public key from a file:

```
usage: vinfra cluster sshkey add <file>
```

<file>

SSH public key file

Example:

This command creates a task to add a public SSH key from the file mykey. pub to the list of trusted keys.

Task outcome:

```
# vinfra task show 100a54ce-0bf5-4bc0-8e46-2e8b952343e6
 Field
         | Value
          | - admin
 args
 kwargs | key: ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAACAQCueW0956J/u5kjWnia7zePChoTMVBtsh1TDNgOskM
           shfHWUzzfydi3/4sTrJ++6dtIoS1D3VVHvHBvp456PT5e/eVy7u0SipOPPoDY2vS2IEY+zjT6MYABi6oEYom
           Dbi7CsRL02HcTWzAkooZNlimWPggYaMT10BZ0KAvNB+Ctpkw8JaT5PRve8UVfjxIQIzL6pQ0f0CDeCHgDsvw
           xK7SrqOvBzTlF9mWkGdTGy+R0JrgGk+v9PvDXZwyeK+qS54uaGmpB6ZRkKMroIk3h+nZ4y/1eQ6m1C8Aspa0
           nnaMaNKOtwOibrd3MDroMcqkJWTTH/cukD3sB+MjL6nmFlrrAfRU6PBkwysIio6/XHS9jG+TI7NeRApkHnwi
           vwIWEKSg6pqaiLUsMi/46KCHzde2Ozg08Hd0R5d7hNN/80mhD7b+bY9wig+VTMoQFQYSWrIy/qLL95ws4amg
           nXOIksNFjfFEE/+lMcZXt3j5kqnjW7OT2/xkqqWoumaM+FEPLNijL18yb29/XJr/cQZX5R9iXSk33DVjhln/
           HG7xpHqAtrXbvKY8zI8t23otGT/rSvWRWV/wgPBZVWSWtsE99FEMmwmxk/b3KuPhi0jK0IUKcv5UBL+NLHw4
           rZRiYgw/fWXPO3f6ZSLLJXtW4iW+BQL60qQWUNQ==
             user@example.com
          | backend.presentation.nodes.ssh.tasks.CreateSshKeyTask
 name
 result
          | id: 6a2fb834-4bc6-4597-ae74-7cacf96b7c75
           key: ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAACAQCueWO956J/u5kjWnia7zePChoTMVBtsh1TDNgOskM
           shfHWUzzfydi3/4sTrJ++6dtIoS1D3VVHvHBvp456PT5e/eVy7u0SipOPPoDY2vS2IEY+zjT6MYABi6oEYom
           Dbi7CsRL02HcTWzAkooZNlimWPggYaMT10BZ0KAvNB+Ctpkw8JaT5PRve8UVfjxIQIzL6pQ0f0CDeCHgDsvw
```

4.3.2 vinfra cluster sshkey list

Show the list of added SSH public keys:

```
usage: vinfra cluster sshkey list
```

Example:

# vinfra cluster sshkey list					
id	key	label			
8ccf7f1b-6a53-4d74-99ce-c410d51a9921 	ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAACA QCueW0956J/u5kjWnia7zePChoTMVBtsh1TDN gOskMg5shfHWUzzfydi3/4sTrJ++6dtIoS1D3 VVHvHBvp456PT5e/eVy7u0SipOPPoDY2vS2IE Y+zjT6MYABi6oEYomIIDbi7CsRL02HcTWzAko oZNlimWPggYaMT10BZOKAvNB+Ctpkw8JaT5PR ve8UVfjxIQIzL6pQOf0CDeCHgDsvwcmxK7Srq OvBzTlF9mWkGdTGy+R0JrgGk+v9PvDXZwyeK+ qS54uaGmpB6ZRkKMroIk3h+nZ4y/1eQ6m1C8A spa0f5nnaMaNKOtwOibrd3MDroMcqkJWTTH/c ukD3sB+MjL6nmFlrrAfRU6PBkwysIio6/XHS9 jG+TI7NeRApkHnwiiOvwIWEKSg6pqaiLUsMi/ 46KCHzde2OzgO8Hd0R5d7hNN/80mhD7b+bY9w ig+VTMoQFQYSWrIy/qLL95ws4amgAQnXOIksN FjfFEE/+lMcZXt3j5kqnjW7OT2/xkqqWoumaM +FEPLNijL18yb29/XJr/cQZX5R9iXSk33DVjh ln/EyHG7xpHqAtrXbvKY8zI8t23otGT/rSvWR WV/wgPBZVWSWtsE99FEMmwmxk/b3KuPhi0jK0 IUKcv5UBL+NLHw4gQrZRiYgw/fWXPO3f6ZSLL JXtW4iW+BQL60qQWUNQ== user@example.com	user@example.com			

This command lists trusted SSH keys.

4.3.3 vinfra cluster sshkey delete

Remove an SSH public key from storage cluster nodes:

```
usage: vinfra cluster sshkey delete <sshkey>
```

<sshkey>

SSH key value

Example:

```
# vinfra cluster sshkey delete 8ccf7f1b-6a53-4d74-99ce-c410d51a9921

+-----+
| Field | Value |

+-----+
| task_id | 053802b2-b4c3-454d-89e2-6d6d312dd2ed |

+-----+
```

This command creates a task to delete the SSH key with the ID 8ccf7f1b-6a53-4d74-99ce-c410d51a9921.

Task outcome:

4.4 Managing External DNS Servers

4.4.1 vinfra cluster settings dns show

Display DNS servers:

```
usage: vinfra cluster settings dns show
```

This command lists the currently used DNS servers: both internal (obtained via DHCP) and external (static set by the user).

4.4.2 vinfra cluster settings dns set

Set DNS servers:

```
usage: vinfra cluster settings dns set --nameservers <nameservers>
```

--nameservers <nameservers>

A comma-separated list of DNS servers

Example:

This command sets the external DNS server to 8.8.8.8.

4.5 Configuring Management Node High Availability

4.5.1 vinfra cluster ha create

Create a HA configuration:

```
usage: vinfra cluster ha create --virtual-ip <network:ip> --nodes <nodes> [--force]
```

--virtual-ip <network:ip>

HA configuration mapping in the format:

- network: network to include in the HA configuration (must include at least one of these traffic types: Internal management, Admin panel, or Compute API);
- ip: virtual IP address that will be used in the HA configuration.

Specify this option multiple times to create a HA configuration for multiple networks.

--nodes <nodes>

A comma-separated list of node IDs or hostnames

--force

Skip checks for minimal hardware requirements

Example:

This command creates a task to create a management node HA cluster from nodes with the IDs 94d58604-6f30-4339-8578-adb7903b7277, f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4, and 7d7d37b8-4c06-4f1a-b3a6-4b54257d70ce.

The command must specify the network with the traffic type Internal management as well as one with the traffic type Admin panel.

Important: After the HA cluster has been created, the admin panel will only be accessible at the provided public IP address. Log in to said address via SSH to continue managing Acronis Software-Defined Infrastructure with the vinfra CLI tool. You may also need to set the VINFRA_PASSWORD environment variable again, because you will access different HA cluster nodes on each log in where it may not have been set.

Task outcome:

4.5.2 vinfra cluster ha join

Join node to the HA configuration:

```
usage: vinfra cluster ha join --nodes <nodes>
--nodes <nodes>
```

A comma-separated list of node IDs or hostnames

Example:

```
# vinfra cluster ha join --nodes 4b83a87d-9adf-472c-91f0-782c47b2d5f1

+-----+

| Field | Value

+-----+

| task_id | 565e9146-254b-4f7a-a2ff-b7119c95baa9 |

+-----+
```

This command creates a task to add the node with the ID 4b83a87d-9adf-472c-91f0-782c47b2d5f1 to the management node HA cluster.

Task outcome:

4.5.3 vinfra cluster ha show

Display the HA configuration:

```
usage: vinfra cluster ha show
```

Example:

```
# vinfra cluster ha show
 Field
                        | Value
 ha_cluster_location | https://10.37.130.200:8888
 nodes
                        | - id: 7d7d37b8-4c06-4f1a-b3a6-4b54257d70ce
                            interface: xxx
                           ipaddr: 10.37.130.103
                            is_primary: false
                          - id: 94d58604-6f30-4339-8578-adb7903b7277
                            interface: xxx
                            ipaddr: 10.37.130.101
                            is_primary: true
                        | - id: f59dabdb-bd1c-4944-8af2-26b8fe9ff8d4
                            interface: xxx
                            ipaddr: 10.37.130.102
                            is_primary: false
                        | - id: 4b83a87d-9adf-472c-91f0-782c47b2d5f1
                            interface: xxx
                            ipaddr: 10.37.130.104
                            is_primary: false
 primary_node_location | https://10.94.41.23:8888
 virtual_ips
                        | - ip: 10.37.130.200
                            roles_set: 6095a997-e5f1-493d-a750-41ddf277153b
                          - ip: 10.94.41.244
                            roles_set: 358bdc39-cd8b-4565-8ebf-e7c12dcd1cf7 |
```

This command shows the management node HA cluster configuration.

4.5.4 vinfra cluster ha release

Relase node from the HA configuration:

```
usage: vinfra cluster ha release --nodes <nodes>
```

--nodes <nodes>

A comma-separated list of node IDs or hostnames

Example:

This command creates a task to release the node with the ID 4b83a87d-9adf-472c-91f0-782c47b2d5f1 from the management node HA cluster.

Task outcome:

4.6 Managing Storage Tier Encryption

4.6.1 vinfra cluster settings encryption show

Display storage tiers encyption:

```
usage: vinfra cluster settings encryption show
```

```
# vinfra cluster settings encryption show
+-----+
| Field | Value |
+-----+
| tier0 | False |
| tier1 | False |
| tier2 | False |
```

```
| tier3 | False |
+----+
```

This command shows encryption status of each storage tier.

4.6.2 vinfra cluster settings encryption set

Set storage tiers encyption:

```
usage: vinfra cluster settings encryption set [--tier-enable {0,1,2,3}]
[--tier-disable {0,1,2,3}]
```

```
--tier-enable {0,1,2,3}
```

Enable encryption for storage tiers. This option can be used multiple times.

```
--tier-disable {0,1,2,3}
```

Disable encryption for storage tiers. This option can be used multiple times.

Example:

```
# vinfra cluster settings encryption set --tier-enable 2
+----+
| Field | Value |
+-----+
| tier0 | False |
| tier1 | False |
| tier2 | True |
| tier3 | False |
+-----+
```

This command enables encryption for the storage tier 2.

4.7 Managing Alerts

4.7.1 vinfra cluster alert list

List alert log entries:

```
usage: vinfra cluster alert list [--all]
```

--all

Show both enabled and disabled alerts

Example:

```
# vinfra cluster alert list --all
 id | type
                     | datetime
                                          | severity | enabled |
  1 | Network warning | 2018-08-30T18:02:14 | warning
  2 | Network warning | 2018-08-30T18:02:14 | warning
  3 | Network warning | 2018-08-30T18:02:14 | warning
  4 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
  5 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
  6 | Network warning | 2018-08-31T13:02:15 | warning
  7 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
    | True
  9 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
 10 | Network warning | 2018-08-31T13:02:15 | warning
      Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
    | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
 12
 13 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
 14 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
 15 | Network warning | 2018-08-31T13:02:15 | warning
                                                     | True
```

This command lists all alerts in the log and shows which alerts are enabled and disabled.

4.7.2 vinfra cluster alert show

Show details of the specified alert log entry:

```
usage: vinfra cluster alert show <alert>
<alert>
```

Alert ID

```
# vinfra cluster alert show 1
 Field
               | Value
              | undefined_speed
 _type
| cluster_id
| cluster_name |
              | 2018-08-30T18:02:14.855302+00:00
 datetime
 details
              | host: stor-1.example.com.vstoragedomain.
 enabled
               | True
 group
 host
               | stor-1.example.com.vstoragedomain.
 id
```

This command shows the details of alert with ID 1.

4.7.3 vinfra cluster alert delete

Remove an entry from the alert log:

```
usage: vinfra cluster alert delete <alert>
```

<alert>

Alert ID

Example:

```
# vinfra cluster alert delete 1
 Field
               | Value
              | undefined_speed
| _type
| cluster_id
 cluster_name |
              | 2018-08-30T18:02:14.855302+00:00
| datetime
 details
               | host: stor-1.example.com.vstoragedomain.
| enabled
               | True
 group
               I node
               | stor-1.example.com.vstoragedomain.
 host
 id
               | Network interface "eth1" on node "stor-1.example.com.vstoragedomain." has an
 message
               | undefined speed
               | 4f96acf5-3bc8-4094-bcb6-4d1953be7b55
| node_id
 object_id
               | eth1
 severity
                warning
 suspended
 type
                Network warning
```

This command deletes the alert with the ID 1 from the log.

4.8 Managing Audit Log

4.8.1 vinfra cluster auditlog list

List all audit log entries:

```
usage: vinfra cluster auditlog list
```

Example:

t vinf	ra cluster	auditlog list			
# vinfra cluster auditlog list ++					
id	username	type	activity	timestamp	
1	admin	LoginUser	 User login	2018-09-07T08:33:44	
2	admin	ChangeNetwrokInterface	Configure network	2018-09-07T09:53:58	
3	admin	UpInterface	Bring up interface	2018-09-07T09:54:44	
4	admin	ChangeNetwrokInterface	Configure network	2018-09-07T09:54:54	
5	admin	CreateBonding	Create bonding	2018-09-07T09:57:24	
17	admin	RemoveNode	Forget node	2018-09-07T12:21:59	
14	admin	RemoveNetworkIface	Delete interface	2018-09-07T12:17:14	
15	admin	RemoveNode	Forget node	2018-09-07T12:17:49	
6	admin	UpInterface	Bring up interface	2018-09-07T10:59:28	
7	admin	ChangeNetwrokInterface	Configure network	2018-09-07T10:59:46	
9	admin	UpInterface	Bring up interface	2018-09-07T11:42:29	
10	admin	UpInterface	Bring up interface	2018-09-07T11:42:42	
11	admin	CreateBonding	Create bonding	2018-09-07T11:43:46	
12	admin	ChangeNetwrokInterface	Configure network	2018-09-07T11:52:17	
13	admin	ChangeNetwrokInterface	Configure network	2018-09-07T11:52:44	
16	admin	RemoveNode	Forget node	2018-09-07T12:21:51	
8	admin	CreateBonding	Create bonding	2018-09-07T11:00:39	
18	admin	RemoveNode	Forget node	2018-09-07T12:22:08	
19	admin	UpInterface	Bring up interface	2018-09-07T12:33:16	
20	admin	CreateVLAN	Create VLAN	2018-09-07T12:34:18	
21	admin	RemoveNetworkIface	Delete interface	2018-09-07T13:26:40	
22	admin	LoginUser	User login	2018-09-07T14:50:06	
23	admin	LoginUser	User login	2018-09-07T14:51:34	
24	admin	CreateNetworkRolesSet	Create custom role set	2018-09-07T15:06:03	
25	admin	ChangeNetworkRolesSet	Configure custom role set	2018-09-07T15:37:50	
26	admin	RemoveNetworkRolesSet	Remove custom role set	2018-09-07T15:39:31	
27	admin	CreateNetworkRole	Create custom role	2018-09-07T15:58:50	
28	admin	RemoveNetworkRole	Remove custom role	2018-09-07T16:20:22	

This command lists the audit log entries.

4.8.2 vinfra cluster auditlog show

Show details of an audit log entry:

```
usage: vinfra cluster auditlog show <auditlog>
```

<auditlog>

Audit log ID

Example:

```
# vinfra cluster auditlog show 1
| Field
            | Value
| activity
          | User login
| cluster_id
| cluster_name |
| component | Users
| details
            | []
| message | User "admin" login
node_id
| result
           | success
 session_id | 817a19beaf244f92604fbf4b40af2c29
task_id | 5686556295049300
| type
            | LoginUser
            I admin
 username
```

This command shows the details of the audit log entry with the ID 1.

4.9 vinfra cluster problem-report

Generate and send a problem report:

```
usage: vinfra cluster problem-report [--email <email>]
[--description <description>] [--send]
```

--email <email>

Contact email address

--description <description>

Problem description

--send

Generate the problem report archive and send it to the technical support team

Example:

This commands creates a task to send a problem report with the description "Test report" to the technical support team and use test@example.com as a reply-to address. Note the problem report ID in the task details. You will need to mention it in the support ticket.

Task outcome:

CHAPTER 5


Monitoring Storage Cluster

Monitoring the storage cluster is very important because it allows you to check the status and health of all computers in the cluster and react as necessary.

The main command for monitoring is vstorage -c <cluster_name> top. It invokes a text user interface that you can control with keys (press \mathbf{h} for help).

5.1 Monitoring General Storage Cluster Parameters

By monitoring general parameters, you can get detailed information about all components of the storage cluster, its overall status and health. To display this information, use the vstorage -c <cluster_name> top command. For example:



The command above shows detailed information about the stor1 cluster. The general parameters (highlighted in red) are as follows.

Cluster	Overall:	status	of the	cluster:
CIUSCCI	Ovciani	Status	OI LIIC	CIUSCCI

healthy	All chunk servers in the cluster are active.
unknown	There is not enough information about the cluster state (e.g., because the master MDS server was elected a while ago).
degraded	Some of the chunk servers in the cluster are inactive.
failure	The cluster has too many inactive chunk servers; the automatic replication is disabled.
SMART warning	One or more physical disks attached to cluster nodes are in pre-failure condition. For details, see <i>Monitoring Physical Disks</i> (page 115).

Space Amount of disk space in the cluster:

free Free physical disk space in the cluster.

allocatable Amount of logical disk space available to clients. Allocatable disk space is calculated on the basis of the current replication parameters and free disk space

on chunk servers. It may also be limited by license.

Note: For more information on monitoring and understanding disk space usage in clusters, see Understanding Disk Space Usage (page 109).

MDS nodes Number of active MDS servers as compared to the total number of MDS servers configured for the cluster.

epoch time Time elapsed since the MDS master server election.

CS nodes

Number of active chunk servers as compared to the total number of chunk servers configured for the cluster.

The information in parentheses informs you about the number of these chunk servers:

- Active chunk servers (avail.) that are currently up and running in the cluster;
- Inactive chunk servers (inactive) that are temporarily unavailable. A chunk server is marked as inactive during its first 5 minutes of inactivity.
- Offline chunk servers (offline) that have been inactive for more than 5 minutes. A chunk server changes its state to offline after 5 minutes of inactivity. Once the state is changed to offline, the cluster starts replicating data to restore the chunks that were stored on the offline chunk server.

License

Key number under which the license is registered on the Key Authentication server and license state.

Replication


Replication settings. The normal number of chunk replicas and the limit after which a chunk gets blocked until recovered.

10 Disks IO activity in the cluster:

- Speed of read and write I/O operations, in bytes per second.
- Number of read and write I/O operations per second.

5.2 Monitoring Metadata Servers

MDS servers are a critical component of any storage cluster, and monitoring the health and state of MDS servers is a very critical task. To monitor MDS servers, use the vstorage -c <cluster_name> top command. For example:



The command above shows detailed information about the stor1 cluster. The monitoring parameters for MDS servers (highlighted in red) are as follows:

MDSID MDS server identifier (ID).

The letter "M" before ID, if present, means that the given server is the master MDS server.

STATUS MDS server status.

%CTIME Total time the MDS server spent writing to the local journal.

COMMITS Local journal commit rate.

%CPU MDS server activity time.


MEM Amount of physical memory the MDS server uses.

UPTIME Time elapsed since the last MDS server start.

HOST MDS server hostname or IP address.

5.3 Monitoring Chunk Servers

By monitoring chunk servers, you can keep track of the disk space available in the storage cluster. To monitor chunk servers, use the vstorage -c <cluster_name> top command. For example:



The command above shows detailed information about the stor1 cluster. The monitoring parameters for chunk servers (highlighted in red) are as follows:

CSID Chunk server identifier (ID).

STATUS Chunk server status:

active The chunk server is up and running.

inactive The chunk server is temporarily unavailable. A chunk server is marked as inactive during its first 5 minutes of inactivity.

offline The chunk server is inactive for more than 5 minutes. After the chunk server goes offline, the cluster starts replicating data to restore the chunks that were stored on the affected chunk server.

dropped The chunk server was removed by the administrator.

SPACE Total amount of disk space on the chunk server.

AVAIL Available disk space on the chunk server.

REPLICAS Number of replicas stored on the chunk server.

UNIQUE Number of chunks that do not have replicas.

IOWAIT Percentage of time spent waiting for I/O operations being served.

IOLAT Average/maximum time, in milliseconds, the client needed to complete a single IO operation

during the last 20 seconds.

QDEPTH Average chunk server I/O queue depth.

HOST Chunk server hostname or IP address.

FLAGS The following flags may be shown for active chunk servers:

J The CS uses a write journal.

C Checksumming is enabled for the CS. Checksumming lets you know when a third party changes the data on the disk.

D Direct I/O, the normal state for a CS without a write journal.

c The chunk server's write journal is clean, there is nothing to commit from the write journaling SSD to the HDD where the CS is located.

5.3.1 Understanding Disk Space Usage

Usually, you get the information on how disk space is used in your cluster with the vstorage top command. This command displays the following disk-related information: total space, free space, and allocatable space. For example:

```
# vstorage -c stor1 top
connected to MDS#1
Cluster 'stor1': healthy
Space: [OK] allocatable 180GB of 200GB, free 1.6TB of 1.7TB
...
```

In this command output:


• 1.7TB is the total disk space in the stor1 cluster. The total disk space is calculated on the basis of used

and free disk space on all partitions in the cluster. Used disk space includes the space occupied by all data chunks and their replicas plus the space occupied by any other files stored on the cluster partitions.

Let us assume that you have a 100 GB partition and 20 GB on this partition are occupied by some files. Now if you set up a chunk server on this partition, this will add 100 GB to the total disk space of the cluster, though only 80 GB of this disk space will be free and available for storing data chunks.

• 1.6TB is the free disk space in the stor1 cluster. Free disk space is calculated by subtracting the disk space occupied by data chunks and any other files on the cluster partitions from the total disk space.

For example, if the amount of free disk space is 1.6 TB and the total disk space is 1.7 TB, this means that about 100 GB on the cluster partitions are already occupied by some files.



allocatable 180GB of 200GB is the amount of free disk space that can used for storing data chunks. See
 Understanding allocatable disk space below for details.


5.3.1.1 Understanding Allocatable Disk Space

When monitoring disk space information in the cluster, you also need to pay attention to the space reported by the vstorage top utility as *allocatable*. Allocatable space is the amount of disk space that is free and can be used for storing user data. Once this space runs out, no data can be written to the cluster.

Calculation of allocatable disk space is illustrated on the following example:

The cluster has 3 chunk servers. The first chunk server has 200 GB of disk space, the second one — 500 GB, and the third one — 1 TB.

• The default replication factor of 3 is used in the cluster, meaning that each data chunk must have 3 replicas stored on three different chunk servers.



In this example, the available disk space is 200 GB, which equals the amount of disk space on the smallest chunk server:

```
# vstorage -c stor1 top
connected to MDS#1
Cluster 'stor1': healthy
Space: [OK] allocatable 180GB of 200GB, free 1.6TB of 1.7TB
...
```

In this cluster configuration each server is set to store one replica for each data chunk. So once the disk space on the smallest chunk server (200 GB) runs out, no more chunks in the cluster can be created until a new chunk server is added or the replication factor is decreased.

If the replication factor changes to 2, the vstorage top command will report the available disk space as 700 GB:

```
# vstorage set-attr -R /mnt/vstorage replicas=2:1
# vstorage -c stor1 top
connected to MDS#1
Cluster 'stor1': healthy
Space: [OK] allocatable 680GB of 700GB, free 1.6TB of 1.7TB
...
```

The available disk space has increased because now only 2 replicas are created for each data chunk and new

chunks can be made even if the smallest chunk server runs out of space (in this case, replicas will be stored on a bigger chunk server).

Allocatable disk space may also be limited by license.

5.3.1.2 Viewing Space Occupied by Data Chunks

To view the total amount of disk space occupied by all user data in the cluster, run the vstorage top command and press the V key on your keyboard. Once you do this, your command output should look like the following:

```
# vstorage -c stor1 top
Cluster 'stor1': healthy
Space: [OK] allocatable 1.32TB of 1.44TB, free 1.39TB of 1.44TB
MDS nodes: 3 of 3, epoch uptime: 19d 23h, cluster version: 128
CS nodes: 3 of 3 (3 avail, 0 inactive, 0 offline), storage version: 128
License: ACTIVE (expiration: 01/10/2021, capacity: 10TB, used: 20.3GB)
Replication: 1 norm, 1 limit
Chunks: [OK] 323 (100%) healthy, 0 (0%) standby, 0 (0%) degraded, 0 (0%) urgent,
            0 (0%) blocked, 0 (0%) pending, 0 (0%) offline, 0 (0%) replicating,
            0 (0%) overcommitted, 0 (0%) deleting, 0 (0%) void
FS: 20.3GB in 757 files, 757 inodes, 244 file maps, 323 chunks, 889 chunk replicas
         read OB/s ( Oops/s), write
                                            0B/s ( 0ops/s)
IO:
                37.1GB (473Kops), write 133.7GB (4.7Mops)
IO total: read
Repl IO: read
                  0B/s, write:
                                  0B/s
Sync rate: 0ops/s, datasync rate: 0ops/s
IO QDEPTH: 0.0 aver, 0.0 max
```

The **FS** field shows the size of all user data in the cluster without consideration for replicas.

5.3.2 Exploring Chunk States

The following is a list of all possible states a chunk can be in.

healthy Number and percentage of chunks that have enough active replicas. The normal state of chunks.

offline

Number and percentage of chunks all replicas of which are offline. Such chunks are completely inaccessible for the cluster and cannot be replicated, read from or written to.

All requests to an offline chunk are frozen until a CS that stores that chunk's replica goes online.

Get offline chunk servers back online as fast as possible to avoid losing data.

blocked

Number and percentage of chunks which have fewer active replicas than the set minimum amount. Write requests to a blocked chunk are frozen until it has at least the set minimum amount of replicas. Read requests to blocked chunks are allowed, however, as they still have some active replicas left. Blocked chunks have higher replication priority than degraded chunks.

Having blocked chunks in the cluster increases the risk of losing data, so postpone any maintenance on working cluster nodes and get offline chunk servers back online as fast as possible.

degraded

Number and percentage of chunks with the number of active replicas lower than normal but equal to or higher than the set minimum. Such chunks can be read from and written to. However, in the latter case a degraded chunk becomes urgent.

replicating

Number and percentage of chunks which are being replicated. Write operations on such chunks are frozen until replication ends.

void

Number and percentage of chunks that have been allocated but never used yet. Such chunks contain no data. It is normal to have some void chunks in the cluster.

pending

Number and percentage of chunks that must be replicated immediately. For a write request from client to a chunk to complete, the chunk must have at least the set minimum amount of replicas. If it does not, the chunk is blocked and the write request cannot be completed. As blocked chunks must be replicated as soon as possible, the cluster places them in a special high-priority replication queue and reports them as pending.

urgent

Number and percentage of chunks which are degraded and have non-identical replicas. Replicas of a degraded chunk may become non-identical if some of them are not accessible during a write operation. As a result, some replicas happen to have the new data while some still have the old data. The latter are dropped by the cluster as fast as possible. Urgent chunks do not affect information integrity as the actual data is stored in at least the set minimum amount of replicas.

standby


Number and percentage of chunks that have one or more replicas in the standby state. A replica is marked standby if it has been inactive for no more than 5 minutes.

overcommitted Number and percentage of chunks that have more replicas than normal. Usually these chunks appear after the normal number of replicas has been lowered or a lot of data has been deleted. Extra replicas are eventually dropped, however, this process may slow down during replication.

deleting Number and percentage of chunks queued for deletion.

5.4 Monitoring Clients

By monitoring clients, you can check the status and health of servers that you use to access virtual machines. To monitor clients, use the vstorage -c <cluster_name> top command. For example:



The command above shows detailed information about the stor1 cluster. The monitoring parameters for clients (highlighted in red) are as follows.

CLID Client identifier (ID).

LEASES Average number of files opened for reading/writing by the client and not yet closed, for the last 20 seconds.

READ Average rate, in bytes per second, at which the client reads data, for the last 20 seconds.

WRITE Average rate, in bytes per second, at which the client writes data, for the last 20 seconds.

RD_OPS Average number of read operations per second the client made, for the last 20 seconds.

WR_OPS Average number of write operations per second the client made, for the last 20 seconds.

FSYNCS Average number of sync operations per second the client made, for the last 20 seconds.


IOLAT Average/maximum time, in milliseconds, the client needed to complete a single IO operation, for the last 20 seconds.

HOST Client hostname or IP address.

5.5 Monitoring Physical Disks

The S.M.A.R.T. status of physical disks is monitored by the smartct1 tool installed along with Acronis Software-Defined Infrastructure. For it to work, S.M.A.R.T. functionality must be enabled in node's BIOS. The tool is run every 10 minutes as a cron job also added during installation. The smartct1 tool polls all physical disks attached to nodes in the cluster, including caching and journaling SSDs, and reports the results to the MDS server.

You can view disk poll results for the last 10 minutes in the output of the vstorage top command. For example:



If the **SMART warning** message is shown in the main table, one of the physical disks is in pre-failure condition according to S.M.A.R.T. Press **d** to switch to the disks table to see more details. For example:

```
Cluster 'stor1': healthy,
Space: [OK] allocatable 100GB (+778GB unlicensed) of 926GB, free 924GB of 926GB
MDS nodes: 1 of 1, epoch uptime: 7d 22h
CS nodes: 2 of 2 (2 avail, 0 inactive, 0 offline)
Replication:
                       1 limit
              1 norm,
                   0B/s (
10:
                           0ops/s), write
                                              0B/s ( 0ops/s)
   DISK SMART
                TEMP CAPACITY
                                        SERIAL
                                                                   MODEL HOST
     sdc
                 270
                        931GB
                                     1374X80PS
                                                      TOSHIBA DT01ACA100 pcs36.ga
     sde
                 31C
                        931GB
                                MSE5235V36ZHWU Hitachi HDS721010DLE630 pcs36.qa
```

The disks table shows the following parameters:

DISK Disk name assigned by operating system.

SMART Disk's S.M.A.R.T. status:

OK The disk is healthy.

Warn The disk is in pre-failure condition. Pre-failure condition means that at least one of these S.M.A.R.T. counters is nonzero:

- Reallocated Sector Count
- Reallocated Event Count
- Current Pending Sector Count
- Offline Uncorrectable

TEMP Disk temperature in Celsius.

CAPACITY Disk capacity.

SERIAL Disk serial number.


MODEL Disk model.

HOST Disk's host address.

To disable S.M.A.R.T. disk monitoring, delete the corresponding cron job.

5.6 Monitoring Event Logs

You can use the vstorage -c <cluster_name> top utility to monitor significant events happening in the storage cluster. For example:



The command above shows the latest events in the stor1 cluster. The information on events (highlighted in red) is given in a table with the following columns:

TIME Time of event.

SYS Component of the cluster where the event happened (e.g., MDS for an MDS server or JRN for local journal).

SEV Event severity.

MESSAGE Event description.

The following table lists basic events displayed when you run the vstorage top utility.

Table 5.6.1: Basic events

Event	Severity	Description
MDS# <n> (<addr>:<port>) lags</port></addr></n>	JRN err	Generated by the MDS master server when it
behind for more than 1000		detects that MDS# <n> is stale.</n>
rounds		This message may indicate that some MDS server is
		very slow and lags behind.

Continued on next page

Table 5.6.1 - continued from previous page

Event	Severity	Description
MDS# <n> (<addr>:<port>) didn't</port></addr></n>	JRN err	Generated by the MDS master server if MDS# <n></n>
accept commits for <i>M</i> sec		did not accept commits for <i>M</i> seconds. MDS# <n></n>
		gets marked as stale.
		This message may indicate that the MDS service on
		MDS# <n> is experiencing a problem. The problem</n>
		may be critical and should be resolved as soon as
		possible.
MDS# <n> (<addr>:<port>) state</port></addr></n>	JRN err	Generated by the MDS master server when
is outdated and will do a full		MDS# <n> will do a full resync. MDS#<n> gets</n></n>
resync		marked as stale.
		This message may indicate that some MDS server
		was too slow or disconnected for such a long time
		that it is not really managing the state of metadata
		and has to be resynchronized. The problem may be
		critical and should be resolved as soon as possible.
MDS# <n> at <addr>:<port></port></addr></n>	JRN info	Generated every time a new MDS master server is
became master		elected in the cluster.
		Frequent changes of MDS masters may indicate
		poor network connectivity and may affect the
		cluster operation.
The cluster is healthy with N	MDS info	Generated when the cluster status changes to
active CS		healthy or when a new MDS master server is
		elected.
		This message indicates that all chunk servers in the
		cluster are active and the number of replicas meets
		the set cluster requirements.

Continued on next page

Table 5.6.1 - continued from previous page

Event	Severity	Description
The cluster is degraded with N	MDS warn	Generated when the cluster status changes to
active, M inactive, K offline CS		degraded or when a new MDS master server is
		elected.
		This message indicates that some chunk servers in
		the cluster are
		inactive, i.e. do not send any registration
		messages, or
		offline, i.e. have been inactive for longer than
		mds.wd.offline_tout, which is 5min by default.
The cluster failed with N active, M	MDS err	Generated when the cluster status changes to
inactive, <i>K</i> offline CS		failed or when a new MDS master server is elected.
(mds.wd.max_offline_cs= <n>)</n>		This message indicates that the number of offline
		chunk servers exceeds mds.wd.max_offline_cs,
		which is 2 by default. When the cluster fails, the
		automatic replication is not scheduled any more.
		So the cluster administrator must take action to
		either repair failed chunk servers or increase
		mds.wd.max_offline_cs. Setting this value to 0
		disables the failed mode completely.
The cluster is filled up to <n>%</n>	MDS info/warn	Shows the current space usage in the cluster. A
		warning is generated if the disk space consumption
		equals or exceeds 80%.
		It is important to have spare disk space for data
		replicas if one of the chunk servers fails.
Replication started, N chunks are	MDS info	Generated when the cluster starts automatic data
queued		replication to recover the missing replicas.
Replication completed	MDS info	Generated when the cluster finishes automatic data
		replication.

Continued on next page

Event	Severity	Description
	_	•
CS# <n> has reported hard error</n>	MDS warn	Generated when the chunk server CS# <n> detects</n>
on <i>path</i>		disk data corruption.
		You are recommended to replace chunk servers
		with corrupted disks as soon as possible with new
		ones and to check the hardware for errors.
CS# <n> has not registered</n>	MDS warn	Generated when the chunk server CS# <n> has</n>
during the last T sec and is		been unavailable for a while. In this case, the chunk
marked as inactive/offline		server first gets marked as inactive. After 5
		minutes, the state is changed to offline, which starts
		automatic replication of data to restore the replicas
		that were stored on the offline chunk server.
Failed to allocate N replicas for	MDS warn	Generated when the cluster cannot allocate chunk
'path' by request from		replicas, for example, when it runs out of disk
<addr>:<port> - K out of M</port></addr>		space.
chunks servers are available		
Failed to allocate N replicas for	MDS warn	Generated when the cluster cannot allocate chunk
'path' by request from		replicas because not enough chunk servers are
<addr>:<port> since only K chunk</port></addr>		registered in the cluster.

Table 5.6.1 - continued from previous page

5.7 Monitoring Replication Parameters

When you configure replication parameters, keep in mind that the new settings do not come into effect immediately. For example, increasing the default replication parameter for data chunks may take some time to complete, depending on the new value of this parameter and the number of data chunks in the cluster.

To check that the new replication parameters have been successfully applied to your cluster:

1. Run the vstorage -c <cluster_name> top command.

servers are registered

2. Press **V** to display additional information about the cluster. Typical command output may look like this:

```
# vstorage -c stor1 top
Cluster 'stor1': healthy
Space: [OK] allocatable 448.6GB of 492.0GB, free 1.39TB of 1.44TB
```

3. Check the **Chunks** field for the following:

- When decreasing the replication parameters, look for chunks that are in the overcommitted or deleting state. If the replication process is complete, no chunks with these states should be present in the output.
- When increasing the replication parameters, look for chunks that are in the blocked or urgent state. If the replication process is complete, no chunks with these states should be present in the output. Besides, when the process is still in progress, the value of the healthy parameter is less than 100%.

For more information on available chunk statuses, see Exploring Chunk States (page 112).

CHAPTER 6

Accessing Storage Clusters via iSCSI


Acronis Software-Defined Infrastructure allows you to export cluster disk space to external operating systems and third-party virtualization solutions in the form of LUN block devices over iSCSI in a SAN-like manner.

In Acronis Software-Defined Infrastructure, you can create groups of redundant targets running on different storage nodes. To each target group you can attach multiple storage volumes with their own redundancy provided by the storage layer. These volumes are exported by targets as LUNs.

Each node in a target group can host a single target for that group if Ethernet is used or one target per FC port if Fibre Channel is used. If one of the nodes in a target group fails along with its target(s), healthy targets from the same group continue to provide access to the LUNs previously serviced by the failed target(s).

You can create multiple target groups on same nodes. A volume, however, may only be attached to one target group at any moment of time.

The figure below shows a typical setup for exporting Acronis Software-Defined Infrastructure disk space via iSCSI.



The figure shows two volumes located on redundant storage provided by Acronis Software-Defined Infrastructure. The volumes are attached as LUNs to a group of two targets running on Acronis Software-Defined Infrastructure nodes. Each target has two portals, one per network interface with the iSCSI traffic type, which makes a total of four discoverable endpoints with different IP addresses. Each target provides access to all LUNs attached to the group. Targets work in the ALUA mode, so one path to the volume is preferred and considered Active/Optimized while the other is Standby. Network interfaces eth0 and eth1 on each node are connected to different switches for redundancy. The initiator, e.g., VMware ESXi, is connected to both switches as well and provides volumes as iSCSI disks 1 and 2 to a VM via different network paths. If the Active/Optimized path becomes unavailable for some reason (e.g., the node with the target or network switch fails), the Standby path through the other target will be used instead to connect to the volume. When the Active/Optimized path is restored, it will be used again.

6.1 iSCSI Workflow Overview

The typical workflow of exporting volumes via iSCSI is as follows:

1. Assign the network with the traffic type iSCSI to a network interface on each node that you will add to a

target group. See "Managing Traffic Types and Networks" in the CLI Reference.

- 2. Create a target group on chosen nodes, providing details for target WWNs and portals. Targets will be created automatically and added to the group. Target portals will be created on specified network interfaces and ports. See *Creating Target Groups* (page 125).
- 3. Create volumes and attach them to the target group. See Managing Volumes (page 66).
- 4. Optionally, enable CHAP authorization for the target group, create CHAP accounts, and assign them to the target group. See *Managing CHAP Accounts* (page 134).
- 5. Optionally, enable ACL authorization for the target group, create a list of initiators that will be allowed to access only specific LUNs. Initiators not on the list will be able to access all LUNs in the target group. See *Managing LUN Views* (page 135).
- 6. Start the target group. See Starting and Stopping Target Groups (page 127).
- 7. Connect initiators to targets using standard tools of your operating system or product, e.g., iscsiadm. Use the vstorage-target session-list command to view iSCSI sessions active on a node in a target group.

6.2 Configuring CLI Tool

Before you can use the vstorage-target CLI tool to export volumes via iSCSI, set it up as described further. Perform these steps on each node where you plan to run iSCSI targets.

1. Create a configuration file /etc/vstorage/iscsi/config.json with at least these mandatory parameters:

```
{
    "ClusterName": "cluster1",
    "VolumesRoot": "/vols/iscsi/vols",
}
```

where ClusterName is the name of your storage cluster and VolumesRoot is the path to the directory for iSCSI volumes.

You can also set these optional parameters:

- "PcsLogLevel", log level, ranges from 1 (log errors only) to 7 (log all, including debug messages),
- "LogPath", path to log files, default is "/var/log/vstorage" (the log will be saved to vstorage-target.log),
- "GetTimeout", the timeout for the initiator's command to read target port group status, default is 3000

ms.

1. Enable the TCM monitor service:

```
# systemctl start vstorage-target-monitor.service
# systemctl enable vstorage-target-monitor.service
```

1. Create the iSCSI volume directory if it does not exist:

```
# mkdir -p /mnt/vstorage/vols/iscsi/
```

If you modify the configuration file later, restart the TCM monitor service to apply changes:

```
# systemctl restart vstorage-target-monitor.service
```

6.3 Managing Target Groups

This section explains how to create and manage groups of iSCSI targets.

6.3.1 Creating Target Groups

Before you create any target groups, assign the network with the iSCSI traffic type to a network interface on each node that you will add to a target group.

To create a target group, you will need a configuration file with a list of nodes to add to the group as well as target WWNs and portals. For example:

In this configuration file:

- NodeId is a node identifier that you can obtain from /etc/vstorage/host_id on a node.
- WWN is a target world wide name:
 - an IQN if iSCSI protocol is used, e.g., iqn.2013-10.com.vstorage:test1 (you can only customize the last part after the colon), or
 - a WWPN in NAA format if Fibre Channel protocol is used, e.g., naa. 21000024ff586d3b (you can obtain the port number from /sys/class/fc_host/host6/port_name).
- Portals is one or more target portals, IP address and port combinations that the target will be accessible at. The IP address Addr is one that belongs to a public network interface on the node that handles the iSCSI traffic type. The port Port is optional and defaults to 3260 if omitted.

Once you have the configuration file, e.g., tg1.json, you can create the target group with the vstorage-target tg-create command. For example, to create an iSCSI target group, run:

```
# vstorage-target tg-create -name tg1 -targets tg1.json -type ISCSI
{
   "Id": "3d8364f5-b830-4211-85af-3a19d30ebac4"
}
```

When you run the command, targets are created on nodes specified in the configuration file and joined to the target group, target portals are created on specified network interfaces and ports.

6.3.2 Starting and Stopping Target Groups

When you create a target group, its targets are initially stopped. You can start them with the vstorage-target tg-start command. For example:

```
# vstorage-target tg-start -id 3d8364f5-b830-4211-85af-3a19d30ebac4
```

This command starts all targets in the group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4.

All targets in a group can either be running or stopped. So if you add targets to a group of running targets, the new targets will be started automatically.

To stop a target group, use the vstorage-target tg-stop command. For example:

```
# vstorage-target tg-stop -id 3d8364f5-b830-4211-85af-3a19d30ebac4
```

6.3.3 Listing Target Groups

You can list target groups with the vstorage-target tg-list command that displays basic information about groups. For example:

```
# vstorage-target tg-list
    "Id": "3d8364f5-b830-4211-85af-3a19d30ebac4",
    "Name": "tg1",
    "Type": "ISCSI",
    "Running": true,
    "ACL": false,
    "ChapAuth": false,
    "CHAP": {},
    "Mode": 0
  },
    "Id": "78c3b51e-fd9a-485b-91ce-bc0a8171c89d",
    "Name": "tg2",
    "Type": "ISCSI",
    "Running": false,
    "ACL": false,
    "ChapAuth": false,
    "CHAP": {},
    "Mode": 0
  }
```

To print complete information about all target groups, use vstorage-target tg-list -all.

6.3.4 Printing Details of Target Groups

To print the details of a specific group, use the vstorage-target tg-status command. For example:

```
# vstorage-target tg-status -id faeacacd-eba6-416c-9a7f-b5ba9e372e16
```

This command prints the complete details of the target group with the ID

faeacacd-eba6-416c-9a7f-b5ba9e372e16. One parameter to pay attention to is NodeState. It indicates whether a node is in sync with the target group, i.e. aware of its current configuration. The following states can be shown:

- synced, node is in sync with the target group,
- syncing, node is syncing with the target group,
- failed, node failed to sync with the target group (see the Error parameter for details),
- · offline, node is offline,
- disabled, node is disabled and its target is offline.

6.3.5 Deleting Target Groups

To delete a target group, use the vstorage-target tg-delete command. For example:

```
# vstorage-target tg-delete -id 3d8364f5-b830-4211-85af-3a19d30ebac4
```

This command deletes the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4.

6.4 Managing iSCSI Volumes

This section describes how to create and manage volumes to be exported via iSCSI.

6.4.1 Creating iSCSI Volumes

To create a volume, use the vstorage-target vol-create command. For example:

```
# vstorage-target vol-create -name vol1 -size 1G \
-vstorage-attr "replicas=3:2 failure-domain=host tier=0"
{
```

```
"Id": "3277153b-5296-49c5-9b66-4c200ddb343d"
}
```

This command creates a 1 GB volume named vol1 on storage tier 0 with 3:2 replication and host as failure domain.

6.4.2 Listing and Printing Details of iSCSI Volumes

To list volumes, use the vstorage-target vol-list command. For example:

```
# vstorage-target vol-list
[
    "3277153b-5296-49c5-9b66-4c200ddb343d",
    "a12110d5-cbbc-498a-acdd-a8567286f927",
    "d5cc3c13-cfb4-4890-a20d-fb80e2a56278"
]
```

Use vstorage-target vol-stat -all to print details of all volumes. To print details of a specific volume, run vstorage-target vol-stat -id <vol_ID>.

6.4.3 Attaching iSCSI Volumes to Target Groups

To attach a volume to a target group, use the vstorage-target tg-attach command. A volume cannot be attached to multiple target groups at the same time. For example:

```
# vstorage-target tg-attach -id 3d8364f5-b830-4211-85af-3a19d30ebac4 \
-volume 3277153b-5296-49c5-9b66-4c200ddb343d -lun 0
```

This command attaches the volume with the ID 3277153b-5296-49c5-9b66-4c200ddb343d to a target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4 as LUN 0. LUN ID numbering must start with 0.

6.4.4 Viewing and Setting iSCSI Volume Parameters

To view and set volume parameters, e.g. redundancy mode, failure domain, or tier, use the commands vstorage-target vol-attr get and vstorage-target vol-attr set, respectively. For example:

```
# vstorage-target vol-attr get -id d5cc3c13-cfb4-4890-a20d-fb80e2a56278
{
   "chunk-size": "268435456",
   "client-ssd-cache": "1",
   "failure-domain": "host",
```

```
"replicas": "3:2",
   "tier": "0"
}
# vstorage-target vol-attr set -id d5cc3c13-cfb4-4890-a20d-fb80e2a56278 \
-vstorage-attr "replicas=2:1 tier=1"
```

6.4.5 Increasing iSCSI Volume Size

To increase the size of a volume, use the vstorage-target vol-grow command. For example:

```
# vstorage-target vol-grow -id d5cc3c13-cfb4-4890-a20d-fb80e2a56278 -size 2G
```

6.4.6 Setting iSCSI Volume Limits

To set read/write limits for a volume, use the vstorage-target vol-limits command. For example:

```
# vstorage-target vol-limits -id d5cc3c13-cfb4-4890-a20d-fb80e2a56278 -read-bps 10485760 \
-write-bps 10485760
```

This command sets read/write speed for the volume with the ID d5cc3c13-cfb4-4890-a20d-fb80e2a56278 to 10485760 bytes per second.

6.4.7 Detaching iSCSI Volumes from Target Groups

To detach a volume from a target group, use the vstorage-target tg-detach command. LUN 0 must be detached last. For example:

```
# vstorage-target tg-detach -id 3d8364f5-b830-4211-85af-3a19d30ebac4 \
-volume d5cc3c13-cfb4-4890-a20d-fb80e2a56278
```

This command detaches the volume with the ID d5cc3c13-cfb4-4890-a20d-fb80e2a56278 from the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4.

6.4.8 Deleting iSCSI Volumes

To delete a volume, use the vstorage-target vol-delete command. You cannot delete volumes attached to target groups. For example:

```
# vstorage-target vol-delete -id d5cc3c13-cfb4-4890-a20d-fb80e2a56278
```

This command deletes the volume with the ID d5cc3c13-cfb4-4890-a20d-fb80e2a56278.

6.5 Managing Nodes

This section describes how to manage nodes in relation to target groups.

6.5.1 Adding Nodes to Target Groups

To add a node to a target group, create a configuration file with details about target WWN and portal. The target will be created automatically on the added node. One node can be added to multiple target groups and the same network interfaces on it can be used simultaneously by multiple targets from different groups.

For example:

```
# vstorage-target node-add -node bbfd0e7a26b1406d -tg 3d8364f5-b830-4211-85af-3a19d30ebac4 \
-targets target.json
```

This command adds the node with the ID bbfd0e7a26b1406d to the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4 and creates a target on it according to the target.json configuration file that looks as follows:

6.5.2 Setting Node Status

To enable or disable a node in a specific target group or all target groups at once, use the vstorage-target node-set command. Enabling a node starts its targets while disabling a node stops its targets and moves the PREFERRED bit to another node.

For example, to enable a node with the ID bbfd0e7a26b1406d in all target groups it belongs to, run

```
# vstorage-target node-set -tg any -node bbfd0e7a26b1406d -enable
```

To disable a node with the ID bbfd0e7a26b1406d in the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4, allowing 60 seconds to move the preferred path to another node (i.e. target), run

```
\# vstorage-target node-set -tg 3d8364f5-b830-4211-85af-3a19d30ebac4 -node bbfd0e7a26b1406d \ -disable -release-timeout 60
```

The release-timeout parameter sets time in seconds that the initiator has to move the preferred (Active/Optimized) path following the PREFERRED bit. If the initiator fails to do so within the given time, the disable operation is cancelled and the node remains enabled. The PREFERRED bit, however, is still moved to another node.

The -force parameter stops the target(s) on the node at once without moving the PREFERRED bit.

6.5.3 Deleting Nodes from Target Groups

To delete a node from a target group, use the vstorage-target node-del command. You can delete nodes only after disabling them in specified target groups. Deleting a node also deletes the targets on that node. For example:

```
# vstorage-target node-del -tg 3d8364f5-b830-4211-85af-3a19d30ebac4 -node bbfd0e7a26b1406d
```

This command deletes the node with the ID bbfd0e7a26b1406d from the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4. The node is already disabled in the target group (see *Setting Node Status* (page 132)).

6.6 Managing Targets and Portals

This section describes how to create and manage targets.

The optimal way is to create a single target per node if you use the iSCSI protocol and one target per FC port if you use the FC protocol.

6.6.1 Creating Targets

Typically, targets are created automatically when you create target groups or add nodes to them. However, as you can delete target(s) from a node without removing the node from a target group, you can also create target(s) on such a node again. Use the vstorage-target target-create command. For example:

```
# vstorage-target target-create -tg 3d8364f5-b830-4211-85af-3a19d30ebac4 -json target.json
```

This command creates a target based on the target.json configuration file in the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4. The configuration file lists target details like the node to create the target on, WWN, and portal. For example:

6.6.2 Adding and Removing Target Portals

To add a portal to a target, use the vstorage-target target-portal add command. For example:

```
# vstorage-target target-portal add -wwn iqn.2013-10.com.vstorage:test2 -addr 10.94.104.90 \
-tg 3d8364f5-b830-4211-85af-3a19d30ebac4
```

This command adds a portal with the IP address 10.94.104.90 and default port 3260 to the target with the IQN iqn.2013-10.com.vstorage:test2 in the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4.

To delete a portal from a target, use the vstorage-target target-portal del command. For example:

```
# vstorage-target target-portal del -wwn iqn.2013-10.com.vstorage:test2 -addr 10.94.104.90 \
-tg 3d8364f5-b830-4211-85af-3a19d30ebac4
```

This command deletes the portal created before.

6.6.3 Deleting Targets

To delete a target from a target group (as well as the node it is on), use the vstorage-target target-delete command. For example:

```
\# vstorage-target target-delete -tg 3d8364f5-b830-4211-85af-3a19d30ebac4 \ -wwn iqn.2013-10.com.vstorage:test22
```

This command deletes the target with the IQN iqn.2013-10.com.vstorage:test22 from the target group with the ID 3d8364f5-b830-4211-85af-3a19d30ebac4 and from the node it is located on.

Nodes that have no targets left on them remain in target groups.

6.7 Managing CHAP Accounts

The Challenge-Handshake Authentication Protocol (CHAP) provides a way to restrict access to targets and their LUNs by requiring a user name and a password from the initiator. CHAP accounts apply to entire target groups. Fibre Channel target groups do not use CHAP.

To use CHAP, enable it for the target group:

```
# vstorage-target tg-auth -enable-chap -id <tg_ID>
```

6.7.1 Creating and Listing CHAP Accounts

To create a CHAP account, use the vstorage-target account-create command. For example:

```
# vstorage-target account-create -user user1 -desc "User for TG1"
Enter Password:
```

The password must be 12 to 16 characters long.

To list existing CHAP accounts and their details, use the vstorage-target account-list command.

6.7.2 Changing CHAP Account Details

To change the password or description of a CHAP account, use the vstorage-target account-set command. For example:

```
# vstorage-target account-set description -user user1 -desc "A new description"
# vstorage-target account-set password -user user1
Enter Password:
```

6.7.3 Assigning CHAP Accounts to Target Groups

To assign a CHAP account to a target group, use the vstorage-target tg-chap command. For example:

```
# vstorage-target tg-chap set -id faeacacd-eba6-416c-9a7f-b5ba9e372e16 -user user1
```

To remove an assignment, run

```
# vstorage-target tg-chap del -id faeacacd-eba6-416c-9a7f-b5ba9e372e16 -user user1
```

6.7.4 Deleting CHAP Accounts

To delete an unused CHAP account, use the vstorage-target account-delete command. For example:

```
# vstorage-target account-delete -user user1
```

6.8 Managing LUN Views

LUN views provide a way to create and manage an access control list (ACL) that limits access to chosen LUNs for specific initiators. Initiators not on the list have access to all LUNs in iSCSI target groups. Volumes exported via Fibre Channel target groups, however, can only be accessed by initiators that are added to group ACL.

To use ACL-based authorization, enable it for the target group:

```
# vstorage-target tg-auth -enable-acl -id <tg_ID>
```

6.8.1 Creating LUN Views

To create a LUN view for an initiator, use the commands vstorage-target tg-initiator add or vstorage-target view-add. The former command adds an initiator to target group's ACL and creates a view for it. The latter command is used to add views to initiators that are already on the ACL.

For example:

```
# vstorage-target tg-initiator add -alias initiator2 -luns 0,1 \
-tg ee764519-80e3-406e-b637-8d63712badf1 -wwn iqn.1994-05.com.redhat:1535946874d
```

This command adds the initiator with the IQN iqn.1994-05.com.redhat:1535946874d to the ACL of the target group with the ID ee764519-80e3-406e-b637-8d63712badf1 and creates a view allowing it to access the LUNs with the IDs 0 and 1.

Another example:

```
# vstorage-target view-add -tg faeacacd-eba6-416c-9a7f-b5ba9e372e16 -lun 2 -map 2 \
-wwn iqn.1994-05.com.redhat:1535946874d
```

This command adds a view for the same initiator allowing it to access LUN 2 as well.

6.8.2 Listing LUN Views

To list LUN views for an initiator, use the vstorage-target view-list command. For example:

```
# vstorage-target view-list -tg ee764519-80e3-406e-b637-8d63712badf1 \
-wwn iqn.1994-05.com.redhat:1535946874d
```

This command lists views for the initiator with the IQN ign.1994-05.com.redhat:1535946874d.

6.8.3 Changing LUN View Details

To change LUN views for an initiator, use the vstorage-target view-set command. For example:

```
# vstorage-target view-set -luns 1 -tg ee764519-80e3-406e-b637-8d63712badf1 \
-wwn iqn.1994-05.com.redhat:1535946874d
```

This command allows the initiator with the IQN iqn.1994-05.com.redhat:1535946874d to access only LUN 1. Essentially, it deletes all LUN views for it excluding specified.

6.8.4 Deleting LUN Views

To delete a LUN view for an initiator, use the vstorage-target view-del command.

```
# vstorage-target view-del -lun 1 -tg ee764519-80e3-406e-b637-8d63712badf1 \
-wwn iqn.1994-05.com.redhat:1535946874d
```

This command deletes the view for LUN 1 for the initiator with the IQN iqn.1994-05.com.redhat:1535946874d.

CHAPTER 7

Advanced Tasks

This chapter describes miscellaneous configuration and management tasks that you may need to perform.

7.1 Updating Kernel with ReadyKernel

ReadyKernel is a kpatch-based service shipped with Acronis Software-Defined Infrastructure and available out-of-the-box on physical servers with active licenses. ReadyKernel offers a more convenient, rebootless alternative to updating the kernel the usual way and allows you not to wait for scheduled server downtime to apply critical security updates. ReadyKernel enables you to receive cumulative kernel patches that fix critical security issues and apply these patches without having to reboot the server. ReadyKernel updates are released for kernels younger than 18 months. When a kernel becomes older that 18 months, you need to switch to a newer kernel to keep receiving ReadyKernel updates.

Upon installation, the patches are loaded into server RAM and immediately applied to the kernel. If the server reboots, these patches are reapplied to the kernel on boot. You can check the details of the applied ReadyKernel patch at any time with readykernel info.

If later you install a new kernel or a major kernel update that requires a reboot, the downloaded patches will remain on the server but will not be applied.

In Acronis Software-Defined Infrastructure, ReadyKernel is set to automatically download and apply updates. Checks for new patches are added to each yum transaction that takes place on any node in the infrastructure.

Even though ReadyKernel requires no user interaction by default, you can read the following subsections to understand how this tool works and manage it if needed.

138

7.1.1 Installing ReadyKernel Patches Automatically

ReadyKernel is enabled by default and checks for new patches daily at 12:00 server time by means of a cron.d script. If a patch is available, ReadyKernel will download, install, and load it for the current kernel.

To disable automatic updating, run

readykernel autoupdate disable

You can re-enable automatic updating later with the following command:

readykernel autoupdate enable <hour>

The service will check for patches daily at the specified <hour> (set in 24-hour format, server time).

7.1.2 Managing ReadyKernel Patches Manually

7.1.2.1 Dowloading, Installing, and Loading ReadyKernel Patches

To download, install, and instantly load the latest ReadyKernel patch for the current kernel, do the following:

- 1. Check for new ReadyKernel patches:
 - # readykernel check-update
- 2. If a new patch is available, download, install, and instantly load it for the current kernel by running:
 - # readykernel update

Note: You can also do this with yum update.

ReadyKernel patches are cumulative, i.e. the latest patch includes all the previous ones. To keep the kernel secure, you only need to install and load the latest patch.

7.1.2.2 Loading and Unloading ReadyKernel Patches

To manually load the latest installed ReadyKernel patch to the kernel, do one of the following:

• If an older patch is already loaded, unload it first, then load the latest patch by running:

- # readykernel load-replace
- If no older patches are loaded, load the latest patch by running:
 - # readykernel load

To unload the patch from the current kernel, run

readykernel unload

7.1.2.3 Installing and Removing ReadyKernel Patches for Specific Kernels

If multiple kernels are installed on the server, you can install a ReadyKernel patch for a specific kernel:

yum install readykernel-patch-<kernel_version>

To remove a specific ReadyKernel patch from the server, run

yum remove readykernel-patch-<kernel_version>

7.1.2.4 Downgrading ReadyKernel Patches

If you experience problems with the latest ReadyKernel patch, you can downgrade it to an older version if one is available.

To downgrade a patch for the current kernel to the previous version, run

yum downgrade readykernel-patch-\$(uname -r)

To downgrade a patch for a specific kernel to the previous version, run

yum downgrade readykernel-patch-<kernel_version>

You can run these commands multiple times to downgrade to the patch version you need. Alternatively, you can downgrade a patch to a specific version by specifying the desired patch version. For example:

yum downgrade readykernel-patch-12.7-0.4-17.vl7

7.1.2.5 Disabling Loading of ReadyKernel Patches on Boot

If for some reason you do not want ReadyKernel patches to be applied at boot time, run the following command:

readykernel autoload disable

To re-enable automatic loading of ReadyKernel patches on boot, run

readykernel autoload enable

7.1.2.6 Managing ReadyKernel Logs

ReadyKernel logs event information in /var/log/messages and /var/log/kpatch.log. You can specify logging parameters for the latter in the configuration file /etc/logrotate.d/kpatch. For more information on parameters you can use, see the logrotate man page.

7.2 Managing Guest Tools

This section explains how to install and uninstall the guest tools. This functionality is required for *Running Commands in Virtual Machines without Network Connectivity* (page 146).

Note: To be able to use the vinfra CLI tool mentioned in this section, you may need to perform steps listed in "Providing Credentials" in the *CLI Reference*.

7.2.1 Installing Guest Tools

To be able to install the guest tools in virtual machines, you first need to create and upload compute images from the supplied guest tools ISO files located in /usr/share/vz-guest-tools/. Execute the following commands on the controller node of your compute cluster:

For Linux guest tools:

```
# vinfra service compute image create vz-guest-tools-lin \
--file /usr/share/vz-guest-tools/vz-guest-tools-lin.iso --os-distro linux
Uploading image to server [Elapsed Time: 0:00:05] ...
```

· For Windows guest tools:

```
# vinfra service compute image create vz-guest-tools-win \
--file /usr/share/vz-guest-tools/vz-guest-tools-win.iso --os-distro windows
Uploading image to server [Elapsed Time: 0:00:09] ...
```

Next, you need to attach the created image to a VM and run the guest tools installer. The steps differ for new and already existing VMs and are described in the following subsections.

7.2.1.1 Installing Guest Tools in New VMs

When you create a new VM, you can attach the guest tools image to it and install the guest tools after the operating system. To do this, perform the following steps on the controller node of your compute cluster:

1. Create a new VM with the guest tools image. For example, to create a Linux VM centos, run:

```
# vinfra service compute server create centos --network id=private --flavor medium \
    --volume source=blank,size=64,boot-index=0,type=disk \
    --volume source=image,id=centos7,size=3,boot-index=1,type=cdrom \
    --volume source=image,id=vz-guest-tools-lin,size=1,boot-index=2,type=cdrom
```

Note: Round up the size of volumes to be created from images. E.g., if the OS distribution image is 2.6 GB, use size=3.

In this example, the first volume is a blank virtual HDD, the second volume is the OS distribution image centos7, and the third volume is the guest tools image vz-guest-tools-lin. Make sure to specify the correct boot order by means of the boot-index parameter.

- 2. Log in to the virtual machine and install an operating system in it.
- 3. Run guest tools installer inside the VM:
 - Inside a Linux VM, create a mount point for the optical drive with the guest tools image and run the installer:

```
# mkdir /mnt/cdrom
# mount /dev/sr1 /mnt/cdrom
# bash /mnt/cdrom/install
```

• Inside a Windows VM, launch the installer in the AutoPlay window if autorun is enabled. Otherwise open the optical drive in Explorer and run setup. exe.

After installing guest tools, restart the VM.

Note: Guest tools rely on QEMU guest agent which is installed alongside the tools. The agent daemon/service gemu-ga must be running for the tools to work.

7.2.1.2 Installing Guest Tools in Existing VMs

The steps you need to perform to install the guest tools in existing VMs depend on the guest OS type. They are described in the following subsections.

7.2.1.2.1 Installing Guest Tools in Existing Linux VMs

To install the guest tools in an existing Linux virtual machine, do the following on the controller node of your compute cluster:

1. Create a volume from the uploaded guest tools image. For example:

```
# vinfra service compute volume create vz-guest-tools-lin-vol --storage-policy default \
--size 1 --image vz-guest-tools-lin
```

2. Attach the guest tools volume to the virtual machine. For example:

3. Log in to the virtual machine, create a mount point for the optical drive with the guest tools image and run the installer:

```
# mkdir /mnt/cdrom
# mount /dev/sdb /mnt/cdrom
# bash /mnt/cdrom/install
```

Note: Guest tools rely on QEMU guest agent which is installed alongside the tools. The agent daemon/service qemu-ga must be running for the tools to work.

7.2.1.2.2 Installing Guest Tools in Existing Windows VMs

To install the guest tools in an existing Windows virtual machine, do the following on the controller node of your compute cluster:

1. Power off the Windows VM. For example, to stop the win10 VM, run:

```
# vinfra service compute server stop win10
```

2. Convert its system volume to a template image. You will need the volume ID that you can obtain with vinfra service compute volume list. For example, to use the win10 VM boot volume, run:

3. Create a new Windows VM from the template, attaching the guest tools image to it during creation. For example:

```
# vinfra service compute server create newvm --network id=private --flavor medium \
    --volume source=image,id=79da5239-b2bb-4779-ada2-46cb8da8ba0e,size=64,boot-index=0,type=disk \
    --volume source=image,id=vz-guest-tools-win,size=1,boot-index=1,type=cdrom
```

Note: The size of volume to be created from a template image must be equal to or greater than the minimum volume size specified in the image metadata. You can learn the minimum volume size by using vinfra service compute image show <image_id> | grep min_disk.

In this example, the first volume is the template of the original VM's system disk and the second volume is the guest tools image. Make sure to specify the correct boot order by means of the boot-index parameter.

4. Once the image is mounted inside the Windows VM, launch the installer in the AutoPlay window if autorun is enabled. Otherwise open the optical drive in Explorer and run setup.exe.

After installing guest tools, restart the VM.

Note: Guest tools rely on QEMU guest agent which is installed alongside the tools. The agent daemon/service qemu-ga must be running for the tools to work.

7.2.2 Uninstalling Guest Tools

The steps you need to perform to remove guest tools depend on the guest OS and are described in the following sections.

7.2.2.1 Uninstalling Guest Tools from Linux VMs

To uninstall the guest tools from a Linux guest, log in to the virtual machine and do as follows:

- 1. Remove the packages:
 - 1. On RPM-based systems (CentOS and other):

```
# yum remove dkms-vzvirtio_balloon prl_nettool qemu-guest-agent-vz vz-guest-udev
```

2. On DEB-based systems (Debian and Ubuntu):

```
# apt-get remove vzvirtio-balloon-dkms prl-nettool qemu-guest-agent-vz vz-guest-udev
```

If any of the packages listed above are not installed on your system, the command will fail. In this case, exclude these packages from the command and run it again.

2. Remove the files:

```
 \begin{tabular}{ll} $\#$ rm -f /usr/bin/prl_backup /usr/share/qemu-ga/VERSION /usr/bin/install-tools $$\etc/udev/rules.d/90-guest_iso.rules /usr/local/bin/fstrim-static /etc/cron.weekly/fstrim-static /etc/cron.weekl
```

3. Reload the udev rules:

```
# udevadm control --reload
```

After removing guest tools, restart the virtual machine.

7.2.2.2 Uninstalling Guest Tools from Windows VMs

To uninstall the guest tools for Windows, log in to the virtual machine and do as follows:

1. Remove QEMU device drivers from the device manager.

Important: Do not remove the VirtIO/SCSI hard disk driver and NetKVM network driver. Without the former, the VM will not boot; without the latter, the VM will lose network connectivity.

- 2. Uninstall QEMU guest agent and guest tools from the list of installed applications.
- 3. Stop and delete Guest Tools Monitor:

```
> sc stop VzGuestToolsMonitor
> sc delete VzGuestToolsMonitor
```

4. Unregister Guest Tools Monitor from Event Log:

```
> reg delete HKLM\SYSTEM\CurrentControlSet\services\eventlog\Application\VzGuestToolsMonitor
```

5. Delete the autorun registry key for RebootNotifier:

```
> reg delete HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Run /v VzRebootNotifier
```

6. Delete the C:\Program Files\Qemu-ga\ directory.

If VzGuestToolsMonitor.exe is locked, close all the Event Viewer windows. If it remains locked, restart the eventlog service:

```
> sc stop eventlog
> sc start eventlog
```

After removing the guest tools, restart the virtual machine.

7.3 Running Commands in Virtual Machines without Network Connectivity

If a VM cannot access a network for some reason, you can still run commands in it from the node the VM resides on. The VM in question must have the guest tools installed in it (see *Managing Guest Tools* (page 141)).

You will need the VM ID that you can obtain with vinfra service compute server list. You can also use a virsh domain name that you can get using virsh list.

7.3.1 Running Commands in Linux Virtual Machines

To run an arbitrary command inside a Linux VM and receive the output to your console, use the virsh x-exec command. For example:

```
# virsh x-exec 1d45a54b-0e20-4d5e-8f11-12c8b4f300db /usr/bin/bash -c 'lsblk'
NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
loop0 7:0 0 945.9M 1 loop
```

```
loop1
            7:1
                        5G 1 loop
 live-rw
          253:0
                  0
                       5G 0 dm
 live-base 253:1
                       5G 1 dm
                  0
            7:2
                  0
                     32G 0 loop
loop2
                  0
                       5G 0 dm
 live-rw
          253:0
                  0
                       64G 0 disk
sda
            8:0
                       1G 1 disk
sdc
            8:32
                  0
sr0
           11:0
                        2G 0 rom /run/initramfs/live
```

To copy a file to a Linux VM, use the virsh x-exec and cat commands. For example:

```
# virsh x-exec 1d45a54b-0e20-4d5e-8f11-12c8b4f300db \
--shell 'cat > test.file' < /home/test.file</pre>
```

To get a file from a Linux VM, use the virsh x-exec and cat commands as well. For example:

```
# virsh x-exec 1d45a54b-0e20-4d5e-8f11-12c8b4f300db \
--shell 'cat /home/test.file' > test.file
```

7.3.2 Running Commands in Windows Virtual Machines

To run an arbitrary command inside a Windows VM and receive the output to your console, use the virsh x-exec command. For example:

```
# virsh x-exec bbf4a6ec-865f-4e2c-ac21-8639d1bfb85c --shell dir c:\\
Volume in drive C has no label.
 Volume Serial Number is D0BE-A8D1
Directory of c:\
                                   24 autoexec.bat
06/10/2009 01:42 PM
06/10/2009 01:42 PM
                                   10 config.sys
07/13/2009 06:37 PM
                       <DIR>
                                      PerfLogs
11/12/2018 07:45 AM
                       <DIR>
                                      Program Files
11/12/2018 07:55 AM
                       <DIR>
                                      test
11/12/2018 06:23 AM
                    <DIR>
                                      Users
11/12/2018 07:53 AM <DIR>
                                      Windows
              2 File(s)
                                    34 bytes
              5 Dir(s) 59,329,495,040 bytes free
```

To copy a file to a Windows VM, use the virsh x-exec and prl_cat commands. For example:

```
# virsh x-exec bbf4a6ec-865f-4e2c-ac21-8639d1bfb85c \
--shell '%programfiles%\\qemu-ga\\prl_cat c:\\test\\test.file' < /home/test.file</pre>
```

To get a file from a Windows VM, use the virsh x-exec and type commands. For example:

```
# virsh x-exec bbf4a6ec-865f-4e2c-ac21-8639d1bfb85c \
--shell 'type c:\\test\\test.file' > test.file
```

7.4 Setting Virtual Machines CPU Model

Virtual machines are created with the host CPU model by default. If nodes in the compute cluster have different CPUs, live migration of VMs between compute nodes may not work or applications inside VMs that depend on particular CPUs may not function properly. To avoid this, you can find out which CPU model offers compatibility across all nodes in the compute cluster and manually set it as the compute cluster default.

Do the following:

- 1. Run virsh capabilities on each node to print an XML document with information on node's CPU. Join the <cpu> sections from all XML outputs to a single XML file, e.g., cpu-compare.xml.
- 2. Compare the CPU features using virsh cpu-baseline. For example:

The command will print the most compatible CPU model across all nodes.

3. Set this CPU model for the compute cluster. For example:

```
# vinfra service compute cluster set --cpu-model IvyBridge
```

Take note of the following:

- For the list of supported CPU models, run vinfra service compute cluster set --help.
- Changing CPU model affects only new VMs (i.e. those created after the change).

See the CLI Reference for more details on the command and information on how to use the vinfra tool.

7.5 Creating Linux Templates

If you do not have a ready Linux template, you can build one with the diskimage-builder tool. The disk image is created with only the root user that has neither password nor SSH keys. You can use the user data and cloud-init methods to perform initial configuration tasks on VMs that will be deployed from the disk image, for example, create custom user accounts. For more options to customize a VM during boot, refer to the cloud-init documentation.

To create a template and deploy a VM from it, do as follows:

1. Install the diskimage-builder package:

```
# yum install diskimage-builder
```

2. For the RHEL 7 guest OS, download the cloud image from the Red Hat Customer Portal (login required) and execute:

```
# export DIB_LOCAL_IMAGE=<path_to_rhel7_image>
```

3. Execute the following command to build a disk image with installed cloud-init for the desired Linux guest. For example:

```
# disk-image-create vm centos7 -t qcow2 -o centos7
```

where

• centos7 is the name of a guest OS. Can be one of the following: centos6, centos7, debian, rhe17, or ubuntu.

By default, using the ubuntu element will create a disk image for Ubuntu 16.04. To build the Ubuntu 18.04 disk image, add the DIB_RELEASE=bionic to the command as follows: DIB_RELEASE=bionic disk-image-create vm ubuntu -t qcow2 -o ubuntu18.

- -o sets the name for the resulting disk image file.
- 4. Upload the created disk image using the vinfra tool to the compute cluster:

```
# vinfra service compute image create centos7-image --os-distro centos7 \
--disk-format qcow2 --file centos7.qcow2
```

where

- centos7-image is the name of a new image.
- centos7 is the corresponding OS version. Can be one of the following: centos6, centos7, debian9, rhe17, ubuntu16.04, and ubuntu18.04.
- centos7.qcow2 is the QCOW2-image created on step 3.
- 5. Create the user-data configuration file with a custom user account:

```
# cat <<EOF > user-data
#cloud-config

users:
    - name: user
```

```
lock-passwd: false
sudo: ALL=(ALL) NOPASSWD:ALL
passwd: $6$CjI58V.q7gFvBlMU$9lvue5t8l/VD/tR9L8VTgaRnIksr7ZkSvjtxGxAelJaa.\
WWAmJwRKLjbJwjikOSO2P5DCEYSX/Uf.MuvvhrCE/
EOF
```

where user is the name of a custom user and \$6\$CjI58V<...> is a hashed password for the account.

6. Launch the deployment of a VM from the disk image using the configuration file as user data:

```
# vinfra service compute server create centos7-vm --flavor medium --network public \
--user-data user-data --volume source=image,id=centos7-image,size=10
```

where

- centos7-vm is the name of a new VM,
- user-data is the configuration file created in step 5,
- centos7-image is the image added to the compute cluster in step 4.

For more information on using the vinfra tool, see Command Line Reference.

7.6 Securing OpenStack API Traffic with SSL

By means of the **Compute API** traffic type, Acronis Software-Defined Infrastructure exposes a public endpoint that listens to OpenStack API requests. By default, it points to the IP address of the management node (or to its virtual IP address if high availability is enabled).

Traffic to and from the endpoint can be secured with an SSL certificate. However, as domain names are not used by default, the certificate will need a subjectAltName field containing the aforementioned management node IP address. If it does not have such a field, you will need to modify the public endpoint to use a domain name that you have a certificate for.

To secure public OpenStack API traffic with SSL, do the following:

- Upload the certificate and then private key in the admin panel, on the SETTINGS > Management node
 SSL ACCESS screen.
- 2. Place the CA certificate file to operating system's trusted bundle:

```
# cp ca.pem /etc/pki/ca-trust/source/anchors/
# update-ca-trust extract
```

Alternatively, you can append the --os-cacert ca.pem option to each OpenStack client call.

3. If your certificate does not have the subjectAltName field, modify all public endpoints to use the domain name for which you have the certificate for. This domain name must resolve to the management node IP address (or to its virtual IP address if high availability is enabled). For example:

```
# openstack --insecure endpoint list | grep public
 44aa0f53a40e4e52b1c7eeeb20c7811e | <...> | https://10.94.16.12:8774/v2.1/%(tenant_id)s
 5a845b4b813047c292db73c42dad5efd | <...> | https://10.94.16.12:8780
| 0b906e518b1041c8b94af7f410403369 | <...> | https://10.94.16.12:9696
 d80af756adf1449f9237c3aeebc9206a | <...> | https://10.94.16.12:8004/v1/%(tenant_id)s
| d0e8c7da7d174e1f9aa4efbc6dff2113 | <...> | https://10.94.16.12:5000/v3
7d901686bca549f9b294e572f046f634 | <...> | https://10.94.16.12:8776/v2/%(tenant_id)s
 1b68ac7c3f7949fbaeef4a815fe6f3b1 | <...> | https://10.94.16.12:8776/v3/%(tenant_id)s
# openstack --insecure endpoint set \
--url https://<DNS_name>:8774/v2.1/%(tenant_id)s 44aa0f53a40e4e52b1c7eeeb20c7811e
# openstack --insecure endpoint set \
--url https://<DNS_name>:8780 5a845b4b813047c292db73c42dad5efd
# openstack --insecure endpoint set \
--url https://<DNS_name>:9696 0b906e518b1041c8b94af7f410403369
# openstack --insecure endpoint set \
--url https://<DNS_name>:8004/v1/%(tenant_id)s d80af756adf1449f9237c3aeebc9206a
# openstack --insecure endpoint set \
--url https://<DNS_name>:5000/v3 d0e8c7da7d174e1f9aa4efbc6dff2113
# openstack --insecure endpoint set \
--url https://<DNS_name>:9292  0e6d3a39d6c44aa883984a35dde434bb
# openstack --insecure endpoint set \
--url https://<DNS_name>:8776/v2/%(tenant_id)s 7d901686bca549f9b294e572f046f634
# openstack --insecure endpoint set \
--url https://<DNS_name>:8776/v3/%(tenant_id)s 1b68ac7c3f7949fbaeef4a815fe6f3b1
```

4. In your OpenRC script, change OS_AUTH_URL to the same domain name and remove all parameters related to insecure access. For example:

```
export OS_PROJECT_DOMAIN_NAME=Default
export OS_USER_DOMAIN_NAME=Default
export OS_PROJECT_NAME=admin
export OS_USERNAME=admin
export OS_PASSWORD=<ADMIN_PASSWORD>
export OS_AUTH_URL=https://<DOMAIN_NAME>:5000/v3
export OS_IDENTITY_API_VERSION=3
```

Now you can run OpenStack commands without the --insecure option.

7.7 Enabling Backup Gateway Geo-Replication

Make sure the following prerequisites are met:

- · Two or more storage clusters with ABGW are deployed.
- All storage clusters are updated to the latest version.
- All storage clusters can ping each other via IP addresses or domain names on port 44445.
- All storage clusters are registered in Acronis Backup Cloud.

To set up geo-replication between two storage clusters, a master and a slave, do the following:

- Find out the dc_uid values from /mnt/vstorage/vols/acronis-backup/conf.d/dc_uid on both the master and the slave.
- 2. Copy the /mnt/vstorage/vols/acronis-backup/certs/abgw.pem files from both the master and the slave to a machine from which you will configure replication (i.e. run vstorage-abgw-ctl). For example, to master_abgw.pem and slave_abgw.pem, respectively.
- 3. Configure replication:

```
# vstorage-abgw-ctl replication \
   --master-addr <master_DNS_name> --master-cert master_abgw.pem --master-uid <master_dc_uid> \
   --slave-addr <slave_DNS_name> --slave-cert slave_abgw.pem --slave-uid <slave_dc_uid> \
   --enable /<account-name>
```

This command will enable replication of existing files. If new files are added to an account, the command will need to be re-run. For more convenience, you can set up a cron job that will run the following script automatically on one of the storage nodes:


```
#!/bin/bash

cd /mnt/vstorage/vols/acronis-backup/storage
for dir in *; do
   vstorage-abgw-ctl replication \
    --master-addr <master_DNS_name> --master-cert master_abgw.pem --master-uid <master_dc_uid> \
    --slave-addr <slave_DNS_name> --slave-cert slave_abgw.pem --slave-uid <slave_dc_uid> \
    --enable /$dir
done
```

If PEM certificates expire, update them in the web interface and exchange them between clusters once again.

If a failover to the slave replica is needed, contact the technical support team. A tool for performing unassisted failovers will be added in a future update.

With geo-replication set up, clusters exchange data as pictured on the diagram.



Where <ext_IP> are external IP addresses of each cluster. The DNS configuration will be as follows:

- primary-storage.mysite.domain will resolve to 1.2.3.4, 1.2.3.5, etc. (external IP addresses of cluster #1)
- secondary-storage.mysite.domain will resolve to 5.6.7.8, 5.6.7.9, etc. (public IP addresses of cluster #2)

In your Acronis Data Cloud admin panel, on the **SETTINGS** > **Locations** screen, you can see configuration like this:

