## 1 Package options

\usepackage[index,hyperref]{litmus} - load the litmus package. Options can be provided as in this example, or later with \litmuscfg{...}.

index=true|false - (default: false) when true, use the index package to add an index of litmus tests.

extern=true|false - (default: false) when true, externalize litmus figures.

hyperref=true|false - (default: false) use the hyperref package to link litmus names with their figures.

strict translation=<true|false> - (default: false) when true, generate an error if a litmus name that needs to be translated includes an edge that has no translation. When false, such edges are copied as is to the translation. default arch=GEN|A64|PPC|RV - (default: GEN) the default architecture in which litmus names are given to \litmus.

target arch=|A64|PPC|RV - (default: empty) if not empty, translate the litmus name given to \litmus to this architecture before typesetting it.

target figs= $\{A64|PPC|RV,...\}$  - (default: empty) which architecture to include in assembly for. empty means the same architecture as target arch.

target events fig=|A64|PPC|RV - (default: empty) which architecture to use for the events diagram. empty means the same as target arch. Note, the default value is not valid if both target arch and default arch also use their default values, as this effectively means target events fig is GEN, which doesn't make sense.

figure placement=... - (default: htb) how to place the figures.

scale events=<factor> - (default: 1)

scale assem=<factor> - (default: 1)

scale full=<factor> - (default: 1)

litmus name=<macro> - <macro> should take 1 argument and typeset it as a litmus name.

litmus ref=<macro> - <macro> should be a macro that takes the following arguments and typesets a reference: #1 is set to the label of the litmus figure; #2 is set to the target architecture; #3 is set to the target name.


append litmus ref=true|false - (default: true) when true, follow the first use of \litmus (or any \litmus+) with the name of the figure where the diagram is (e.g. "MP (Figure 1.1)").

context=<name> - (default: main) The *context* becomes part of the reference name of the litmus test. This is useful when you want to include the same test multiple times. (context is also prefixed to hyperref links and the externalised name).

exp results midrule=|none|<n> - (default: 5) in experimental result tables, draw a midrule every few lines. none disables this option; <n> draw every n lines; when empty, re-enable the option.

### 2 Macros

\litmus{<name>} - adds a figure of the litmus, if one does not already exist, typesets the litmus name and hyperlinks it to the figure, like this: MP (Figure 1).



<u>MP</u>	Power
Thread 0	Thread 1
li r1,1 stw r1,0(r2)//3 li r3,1 stw r3,0(r4)//3	lwz r1,0(r2)//c a lwz r3,0(r4)//d
Initial state: 0:r4=y; 0:r2=x; 1:r4=x; 1:r2=y;	
Allowed: 1:r1=1; 1:r3=0;	

MP	AArch64
Thread 0	Thread 1
MOV W0,#1 STR W0,[X1] //a MOV W2,#1 STR W2,[X3] //b	LDR W0,[X1] //c LDR W2,[X3] //d
Initial state: 0:X3=y;	
0:X1=x; 1:X3=x; 1:X1=y;	
Allowed: 1:X0=1; 1:X2=0;	
MP	RISC-V
Thread 0	Thread 1
sw t0, 0(t1)//a sw t0, 0(t2)//b	lw t0, 0(t1)//c lw t2, 0(fp)//d
Initial state: 0:x7=y; 0:x6=x;	
0:x5=1; 1:x8=x; 1:x6=y;	
Allowed: 1:x5=1; 1:x7=0;	

Figure 1: Litmus test MP

\litmus+{<name>} - similar to \litmus{<name>} except that it forces a new figure, even if a previous one already exists.

\litmus-{<name>} - similar to \litmus{<name>} except that it never adds a figure (for forward referencing).

\litmus\*{<name>} - just typesets the litmus name (without a figure or a link), like this: MP.

### 3 litmuscfg

The followings are options that can be changed by \litmuscfg{<options>}.

index - can only be used in the preamble. Loads the index package and generates an index of litmus tests (use \printindex[litmus] to typeset the index).

hyperref - can only be used in the preamble. Loads the hyperref package and links litmus names to their figures. extern=false|true - (initially false, default true) can only be used in the preamble. Externalise the litmus figures, that is, generates a separate pdf for each diagram (once), and then include those pdf in the document instead of typesetting them every time the document is built.

strict translation=false|true - (initially false, default true) be strict when translating litmus name between architectures (strict will fail if an edge has no mapping, non-strict will use the source name of the edge).

default arch=<arch> - (initially GEN) the default value of the optional argument of \litmus. For example, \litmus\*{MP+fens} parses the litmus name as a generic (GEN) name and \litmus\*[A64]{MP+dmb.sys} parses the litmus name as an AArch64 name.

target arch=<arch> - (initially empty) the target architecture of litmus names of  $\lower=$  as the source arch). For example  $\lower=$  arch=PPC $\lower=$  arch=PPC $\lower=$  will translate the AArch64 name MP+dmb.sys to the Power name MP+syncs.

target figs=<archs> - (initially empty) a CSV of the architectures that are to appear in litmus diagrams (empty means same as the source arch).

litmus ref=<macro> - (initially equivalent to \ref{#1}) <macor> should take three arguments and typeset a reference to a litmus figure. The arguments are: #1 - label of the litmus figure; #2 - target architecture; #3 - target name.

<code>context=<name> - (initially main)</code> by changing context you can include multiple figures of the same litmus test and reference each one specifically.

exp results midrule=none|<n> - (initially none) determines if a midrule should be drawn every <n> lines in experimental results tables. With no argument the option is enabled with the previous value of <n> (initially 5).

### 4 litmus.names.cfg

This file defines how litmus names are translated between architectures.

The translation does not change the basic shape name (e.g. MP), which is the prefix of the name made of anything that is not a lower case letter, but not including the last '+' if the prefix ends with one (e.g. the name of 2+2W+dmb.sys is 2+2W).

The suffix of the name is then split to edges, separated by '+' and '-', And each edge is translated according to the mapping.

<name> and target architecture <trq>. For example: \newlitmusnametrans{GEN}{MP+addrs}{A64}{MP+addrs+V2}.

 $\label{lem:limusnametrans} $$ \operatorname{-src}{{\rm ame}} {<\rm src} {<\rm src}$ 

# **Index of Litmus Tests**

Numbers written in bold refer to the page where a figure of the litmus test is displayed.

# All architectures MP, 1 MP+dmb.sys, 2 MP+syncs, 2 Generic MP, 1, 1, 2 AArch64 MP, 1 MP+dmb.sys, 2 Power MP, 1 MP+syncs, 2 RISC-V MP, 1