The response format when an error occurs is shown below.

message	code	body	type	required(Allow nul	Allow empty		remarkss
response		error_code		0	×		A value that represents details of an error that occurred in the MFC / FC	Refer to the table below for the format
		error_message	string	0	×		Failure cause (exception message)	-
		data_consistency	string	0	×		Data integrity state	By this error occurrence, it indicates whether the data has returned to the pre-request state, returned to the requested state, or inconsistent state. MFC case: data consistency between clusters In the case of FC: data consistency between CTLs / devices in the cluster Returned to the pre-request state: "rolled back" Transited to post-request state: "updated" Inconsistent state: "not consistent"
		target_clusters	object[]	×	O ×	0	All cluster information requested Cluster ID to be processed	For MFC: When an error occurs in FC, set this parameter. Returning the status of all clusters, including the cluster in which no erro occurred. For FC: This parameter can be omitted
		cluster_id	string	0	×	$\overline{}$	Gluster ID to be processed	-
		request_results	string	0	×		Request result	Responds to the request for each cluster unit. Success: "success' Failure: "failed"
		error_code	string	×	0		A value that represents details of an error that occurred in the MFC / FC	failed.
		error_message	string	×	0		Failure cause (exception message)	Responds when the request result of the processing target cluster is
		data_consistency	string	0	×		Data integrity state	Indicates the matching state of data between CTLs / devices in the cluster due to error occurrence. Returned to the pre-request state: "rolled back" Transited to post-request state: "updated" Inconsistent state: "not consistent" Unknown state: "unknown"

Body uses JSON format.

 $\frak{\%}1$ The response code is set depending on the generated error.