

# Data definition language (DDL)

# **Data definition language**

The sublanguage responsible for defining how data are structured in a database in SQL is called the **data definition language (DDL)**.


The commands that are used to **build, amend, or remove** SQL tables are contained in the data definition language.


These commands include **CREATE TABLE**, **ALTER TABLE**, **TRUNCATE TABLE**, **and DROP TABLE**.

# **Database schemas and tables**

Tables are the fundamental building blocks of a database schema and **store data in rows and columns**.

A database schema is a **logical container that houses these tables** and provides a framework for classifying, ordering, and arranging them in **relation to one another**.





3

# **Database schemas and DDL**

A SQL sublanguage known as **data definition language**, or **DDL**, is used to **create**, **modify**, **or remove** SQL tables from the database schema.

```
CREATE DATABASE united_nations;
USE united_nations;

CREATE TABLE united_nations.Access_to_Basic_
Region VARCHAR(32),

ALTER TABLE Access_to_Basic_Services
MODIFY COLUMN Country_name VARCHAR(37);

DROP TABLE Access_to_Basic_Services;
DROP DATABASE united_nations;
```

# **CREATE DATABASE**

The CREATE DATABASE statement is used to create a new SQL database.

### Syntax

CREATE DATABASE database\_name;
USE database\_name;

Creating a database typically **requires appropriate permissions or privileges** depending on the database management system we are working with.

Example

- 2 USE united\_nations;

- 1. Creates a database named united\_nations.
- 2. Selects the united\_nations database.

  All subsequent SQL operations will be performed inside this database.

# **CREATE TABLE**

The CREATE TABLE statement is used to **create new** tables. It specifies the structure of the table, defining the columns and their data types.

# **Syntax** CREATE TABLE table\_name ( column1 datatype. Column2 datatype [Constraint], . . . . ); Creates a table inside the united\_nations database named Access to Basic Services. If the "USE database\_name" function wasn't executed, the database name is entered before the table name. Inside the brackets, it defines the name of each **column** and its **data type** separated by a comma.

```
CREATE TABLE united_nations.Access_to_Basic_Services(
Region VARCHAR(32),
Sub_region VARCHAR(25),
Country_name INTEGER NOT NULL
Time_period INTEGER NOT NULL,
Pct_managed_drinking_water_services NUMERIC(5,2),
Pct_managed_sanitation_services NUMERIC(5,2),
Est_population_in_millions NUMERIC(11,6),
Est_gdp_in_billions NUMERIC(8,2),
Land_area NUMERIC(10,2),
Pct_unemployment NUMERIC(5,2)

After the data type, we can insert an optional
```

After the data type, we can insert an optional constraint that allows us to enforce rules on the type of data the column can have, e.g. NOT NULL.

# **Constraints**

When creating a table in SQL, we can apply various **constraints** to columns to **enforce data integrity** and **define rules** for the values stored in those columns. Here are some commonly used constraints in SQL:

### NOT NULL

This constraint ensures that a column **cannot contain NULL values**. It enforces the requirement for the column to have a non-null value for each row.

# PRIMARY KEY

The PRIMARY KEY constraint **uniquely identifies each row in a column** combining the **NOT NULL and UNIQUE** constraints. The primary key column values are unique and cannot be null.

### UNIQUE

This constraint ensures that the values in a column (or a combination of columns) are **unique across the table**. It **prevents duplicate values** from being inserted into the column(s).

### FOREIGN KEY

This constraint **establishes a relationship between two tables** based on a column. It ensures that the values in the **primary key column** in the first table **correspond** to the values in the **foreign key column** in the second table.

# **ALTER TABLE**

The ALTER TABLE statement is used to **modify the structure of an existing database object**, such as adding, modifying, or deleting columns in a table.

# **Syntax** To add a column ALTER TABLE table\_name ADD column\_name datatype; To delete a column ALTER TABLE table\_name DROP COLUMN column\_name; To rename a column ALTER TABLE table name **RENAME COLUMN** old\_name to new\_name; To change the data type of a column ALTER TABLE table name **MODIFY COLUMN** column\_name datatype:

```
-- Add column Gini_index with datatype FLOAT
ALTER TABLE Access_to_Basic_Services
ADD Gini_index FLOAT;

-- Drop column Gini_index
ALTER TABLE Access_to_Basic_Services

DROP COLUMN Gini_index;
```

```
ALTER TABLE Access_to_Basic_Services

MODIFY COLUMN Country_name VARCHAR(37);
```

# TRUNCATE TABLE

The TRUNCATE TABLE statement is used to **remove all data from a table**, effectively resetting it to an empty state. This operation is faster than deleting individual rows.

### **Syntax**

TRUNCATE TABLE table\_name;

\*If the "USE database\_name" function wasn't executed, the database name is entered before the table name.

As soon as the TRUNCATE TABLE statement is executed, the data are **permanently wiped from the table** and **cannot be recovered**, hence it is important to use this command with caution. Appropriate backups of the data are required.

Example

TRUNCATE TABLE united\_nations.Access\_to\_Basic\_Services:

Removes all the content of the Access\_to\_Basic\_Services table without deleting the table itself

# DROP TABLE and DROP DATABASE

The DROP statements are used to **remove entire database objects**, such as tables or schemas, from the database.

# DROP TABLE table\_name; DROP DATABASE database\_name;

Example

DROP TABLE Access\_to\_Basic\_Services;
DROP DATABASE united\_nations;

It is important to exercise caution when using the DROP TABLE or DROP DATABASE statements as they permanently delete the table or database, and they cannot be recovered.

Deletes the Access\_to\_Basic\_Services table and then deletes the united\_nations database as well.