



Concepts Manual

Version 2.6

October, 2013

Prepared By:

Zethcon Corporation
200 W 22nd Street
Suite 218
Lombard, IL 60148

Manual Notes	1
Customer Setup	2
Customer Definition.....	2
Customer/Name	3
Additional Buttons	7
Customer/Receiving.....	8
Customer/Receiving/Options	8
Customer/Receiving/Options 2.....	15
Customer/Receiving/Confirmation	21
Customer/Receiving/Instructions.....	25
Customer/Receiving>Returns	25
Customer/Receiving/ABC Cycle.....	27
Customer/Receiving/Suppliers	29
Customer/Receiving/Facility Returns Disposition	30
Customer/Receiving/Overage	31
Customer/Receiving/Inventory Status Change	32
Customer/Shipping	33
Customer/Shipping/Options-1	33
Customer/Shipping/Options-2	40
Customer/Shipping/Options-3	45
Customer/Shipping/Options-4	48
Customer/Shipping/Options-5	54
Customer/Shipping/Instructions	55
Customer/Shipping/BOL Comments	56
Customer/Shipping/Pack List	57
Customer/Shipping/Audit Locations	60
Customer/Shipping/Carriers	60
Customer/Shipping/Notification	61
Customer/Shipping/SIP Settings and Consignee	63
Customer/Shipping/TMS	64
Customer/Shipping/Custom BOL #	65
Customer/Shipping/Carrier Note	66
Customer/Billing.....	66
Customer/Dictionary.....	67
Customer/Labeling.....	68
Customer/Labeling/General	68
Customer Labeling/Labeling Options.....	68
Customer/Facility Settings.....	70
Customer/Handling	72
Customer/Trading Partners	73
Item setup	75
Item Specs/Name	75
Item Specs/UOM	80
Item Specs/Specs	84
Item Specs/Receiving.....	88

Item Specs/Receiving/Options – 1	88
Item Specs/Receiving/Options – 2	94
Item Specs/Receiving/Instructions.....	96
Item Specs/Receiving/Format Validation	98
Item Specs/Shipping	98
Item Specs/Shipping/Options – 1.....	98
Item Specs/Shipping/Options – 2.....	102
Item Specs/Shipping/Ship To Expiration.....	104
Item Specs/Shipping/Instructions	105
Item Specs/Shipping/BOL Comments	106
Item Specs/Labeling.....	106
Item/Specs/Labeling/General.....	106
Item/Specs/Labeling/Labeling Options	107
Item Specs/Hazardous.....	109
Item Specs/Hazardous/DOT	109
Item Specs/Hazardous/SARA	111
Item Specs/Handling.....	112
Item/Aliases	114
Item/Storage	115
Item/Substitutes.....	116
Item/Pick Fronts.....	117
Item/Facility Settings	119
Facility Setup.....	120
Definition	120
Facility/Facility Maintenance	121
Facility Maintenance/Name	121
Facility Maintenance/Remit to Address.....	124
Facility Maintenance/Options.....	125
Facility Maintenance/Scheduler.....	127
Facility Maintenance/Tender	129
Location Setup.....	130
Setup/Facility/Location/Location Maintenance.....	130
Location Maintenance/Definition	130
Location Maintenance/Zones	136
Location Setup Wizard and Location Expert.....	137
Section Setup.....	138
Setup/Facility/Location/Section Maintenance	138
Zone Setup.....	143
Setup/Facility/Location/Zones	143
Allocation Rules Setup.....	146
Setup/Facility/Allocation Rules	146
Allocation Rule Details Maintenance	147
Frequently Asked Questions about Allocation and Task Generation.....	152
Putaway Profiles Setup	154

Setup/Facility/Putaway Profiles.....	154
Putaway Profile Rule Maintenance.....	155
Additional Information on Multi-Plate Putaway	162
Additional Putaway Notes	163
Carrier Code Setup.....	165
Carrier Maintenance/Name	165
Carrier Maintenance/Staging Locations	167
Carrier Maintenance/Delivery Service	169
Carrier Maintenance/Pro Numbers	170
Facility Setup	170
Customer Setup.....	172
Carrier Setup	173
Carrier Maintenance/Notification	176
Security for Carrier Maintenance.....	177
Security Setup.....	178
Overview.....	178
Group	178
Individual User.....	178
Adding a Group.....	178
Group Info Tab	180
Info Tab.....	183
Updating a Group.....	184
Adding an Individual User.....	186
User Info Tab	187
Info Tab.....	188
Customer/Facilities Tab	190
User Overrides	191
Updating an Individual User.....	193
Cloning Group Settings and User Overrides	195
Cloning Group Settings.....	195
Cloning User Overrides	196
Additional Requirements for RF Users.....	197
RF Task-Level Privileges Set on the Employee Information Screen	198
CRT Form ID Chart	199
RF Form ID Chart.....	205
Frequently Asked Questions	208
Miscellaneous Setup Topics.....	210
Damaged Item Codes.....	210
Customer Specific Validation Tables	210
Class_to_Company_CCCCCCCCCC	210
Class_to_Warehouse_CCCCCCCCCC	211
EDI_Parameters_for_CCCCCCCCCC	212
EDI_Parameters_for_CCCCCCCCCC_WWWW.....	213
SAP Parameters	214
Default Values Setup	217

Setup/Default Values	217
Default Values Chart.....	218
Validation Tables	234
Setup/Validation Tables.....	234
Validation Table Maintenance.....	235
Validation Table Chart.....	235
Appendix A - <i>Chart of Business Events</i>	243
Obsolete Business Events – Not supported in current versions of SYNAPSE.....	247
Appendix B - <i>Chart of RF Employee Activity</i>.....	249

Manual Notes

This manual is composed of 2 documents:

File Name	File Type	Description
SYNAPSE Concepts.doc	PDF	Cover Page, TOC and Manual
App B – rf employee activities.xls	MS Excel	Appendix B – Chart of RF Employee Activity; Please place behind Appendix title page at the back of the manual.

The Billing information that was included in previous versions of this manual is in the SYNAPSE Billing Concepts Manual.

Zethcon Corporation has made every effort to ensure the accuracy of the information included in this document. This document is subject to change without notice.

Please address any questions or comments to support@zethcon.com.

Customer Setup

Customer Definition

It is important to understand the difference between a customer, a consignee and a supplier in SYNPASE.

- A ***Customer*** is the warehouse's client or the company that owns the merchandise.
- A ***Consignee*** is a customer's customer or the person or company receiving the merchandise.
- A ***Supplier*** provides goods for a customer.

For example, XXX Industries manufactures and sells picnic tables and they store the merchandise at this facility and ship the merchandise from this facility. XXX Industries is considered a “**customer**”. This facility ships XXX-brand picnic tables to individual AAA Super Stores. Each AAA Super Store is considered a distinct “**consignee**”. XXX Industries also sells table umbrellas but they are manufactured and delivered to this warehouse by ZZZ Company. ZZZ Company would be considered a “**supplier**” for XXX Industries.

Note: Many of the values set up on this series of screens become the customer-default values used by Product Group and Item screens.

Customer/Name

The screenshot shows the Zethcon Customer Management System interface. The main title bar reads "Customer INA-The Food Countess". The top menu bar includes "Name", "Receiving", "Shipping", "Billing", "Dictionary", "Labeling", "Facility Settings", "Handling", and "Trading Partners". Below the menu, there are tabs for "Customer ID: INA" and "Status: Active". The main form fields include:

- Name:** The Food Countess
- Lookup:** INA
- Contact:** Ashley
- Address:** 333 Main St.
- City:** Lincoln
- Postal Code:** 45678
- Country:** USA
- E-Mail:** sally.winchell@zethcon.com
- Primary CSR:** Ashley Thomas
- Phone:** (empty)
- FAX:** (empty)
- Consumables Owner:** CON
- Rates:** (button)
- Groups:** (button)
- Items:** (button)

On the right side, there are several checkboxes and radio buttons for configuration:

- Use Expanded WebSynapse fields
- Suppress Anniversary Date
- Aggregate Inventory
- Require Cycle Count Item
- Require Cycle Count Lot
- Require Physical Inventory Item
- Require Physical Inventory Lot
- Use Labels
- Allow Extra Picking
- Allow Load Assignment

Below these are sections for "Track Pallets", "Bill For Pallets", "Duplicate Order Reference Allowed", "Unique Order Identifier", and "Reduce Order Qty By Cancel Amount".

The "Additional Contacts" section contains five rows for entering phone numbers, FAX numbers, and e-mails.

At the bottom, there are fields for "Customer Logo" (set to "barefootcontessa") and "Default Order Attachment Directory" (with a browse button "...").

A status bar at the bottom left shows "LINUXTEST Facility ZET (Last Update by ANN at 10/18/2013 01:06 PM)".

Customer ID

The customer ID must be unique for each customer. The field is alphanumeric. Hyphens are allowed. **Do not use special characters such as &, ‘, “, % in the customer id.**

Status

Values are maintained in the 'CustomerStatus' validation table.

Name

This field contains the name of the customer.

Lookup

This field can contain an abbreviated or alternate customer name to be used while using the customer lookup process.

Contact

This field contains the name of the primary contact for the customer account.

Address Info

These fields contain the primary address information for the customer. This is the default billing information when billing addresses aren't specified by bill type.

Phone

The customer's phone number.

Fax

This is used as an informational only field and there are no formatting requirements.

Email

This field is used to indicate the primary email address for the customer. There are no edits to check for proper formatting. Additional addresses can be added separated by a semi-colon.

Primary CSR

This indicates the primary Customer Service Representative for the customer account. This value is selected from the individual users in the security table.

Consumables Owner

This is used to indicate an Aggregate Inventory Customer where inventory such as empty barrels, finishing materials, etc. is tracked. See the Synapse User Manual chapter on Aggregate Inventory for additional information about consumables processing.

Use Expanded WebSynapse Fields

This allows WebSynapse to display Customer Dictionary Values for Header and Detail Pass Thru Fields.

SUPPRESS ANNIVERSARY DATE

This option supports customers that do not use any anniversary date tracking for billing or for LIFO/FIFO tie breaking allocation rules that may result in the anniversary date being the tie breaker. With this option checked, if plate consolidation is needed, the anniversary date is not considered as part of the inventory characteristics that the consolidation routines check in the following options:

- 1-Step Receipt (option 11)
- Build Pallet (option 13)
- Damaged Items (option 96)
- Dekit (option 64)
- Detail Return (option 23)
- Kitting (option 63)
- RF option 82
- Right-clicking an MP in Plate Lookup followed by selecting Consolidate Plate from the menu

When multiple plates are consolidated, the newest anniversary date will be used. When one LP is added to another, the added-to LP will retain its anniversary date.

This setting overrides the system default “SUPPRESSANNIVERSARYDATE”

Aggregate Inventory

If this box is checked, this customer uses the Aggregate Inventory functionality for Receiving, Shipping and Inventory Control.


Use Labels

If this box is checked, the user will be asked at wave release for pick label printing parameters.

Allow Extra Picking

If this box is checked, additional non-tasked item entries will be allowed on the Ship Order Screen. The entries must exist on the order.

Allow Load Assignment

If this box is checked, the Assign to load button  on the Order Information screen will function as it does for non-Aggregate Inventory customer orders, allowing load assignment on outbound orders. The Load Information screen will allow you to close loads for shipped Aggregate Inventory orders.

For more information on Aggregate Inventory processing, see the SYNAPSE User Manual.

Require Cycle Count Item

If the "Require Cycle Count Item" is set, when you cycle count LPs if you do not enter an item (and customer) and on the LP, you will get an error message. If the flag is not set, then the customer, item, description and lot are displayed and the you can either just press enter or override any of the fields (except for description).

Require Cycle Count Lot

When this option is checked, the count tasks will follow the normal cycle count requirements for lot. When the option is unchecked, the lot number will appear on the screen during a cycle count and you won't have to enter it.

Require Physical Inventory Item

When this check box is selected, the RF operator will be required to enter all the data elements for the LP being counted, such as Customer, Item and Lot. This is the default functionality for Physical Inventory processing. When the check box is NOT selected, the data will be auto populated when the LP is scanned. This feature works similar to the Require Cycle Count Item option.

Require Physical Inventory Lot

When this option is checked, the Physical (PI) tasks will follow the normal PI requirements for lot. When the option is unchecked, the lot number will appear on the screen during a cycle count and you won't have to enter it.

Track Pallets

If this box is checked, pallet-tracking information must be entered prior to closing a load – either inbound or outbound.

Collect Pro Numbers

If this box is checked, pro numbers must be entered for all outbound orders for this customer prior to closing a load.

Allow Pick Passing

If checked, this functionality allows an operator to drop a pallet he is picking and another operator (or the same operator) can resume picking to the pallet. This is called Pick Passing. When the operator drops the picked pallet, they will be prompted for the location (this should be a P&D location) and also prompted for Allow Passing (they must answer Yes). Then an operator performs a Resume Pass (RF Option 47) to pick up the pallet and continue picking the order.

If Allow Pick Passing is unchecked for the customer, then these 2 fields will not be displayed regardless of any unpicked picks.

Bill for Pallets

This is an informational-only field to be used for pallet tracking billing purposes.

Duplicate Order Reference Allowed

If the Duplicate Order Reference Allowed radio button is set to:

- Warn - the operator will receive a warning message during order entry, order update or when duplicating an order if the same reference number exists on another order.
- No - the operator will receive a message and the order cannot be added, updated or duplicated if the same reference number exists on another order.
- Hold - the order is added and put in Hold status if the same reference number exists on another order. A message is created in the message queue that can be used to alert an appropriate individual so that action can be taken.

Unique Order Identifier

Reference/Reference and PO radio buttons. This is used for EDI update identification and determines the unique key for the order.

Master Account

This indicates the customer ID for a master account for pallet tracking.

Manufacturer UCC Code

This data is used in creating the SSCC-18 code for a shipping unit.

Recent Order Days

The Order Lookup Form and TMS Order Lookup Form have a “Recent Orders” check box. When checked, the system only searches for orders that are in an open status or for closed orders that have been processed within a recent time period. The time period is determined by the value entered here. If the “Recent Orders” check box is not set, the Order Lookup performs its search against the entire database.

Min 0 Qty Weight

If a plate exists with no quantity and still has an existing weight (i.e., catch weight items), this parameter allows the plate to be automatically deleted if it is below the minimum weight set. The weight is an absolute value and can be set for whole numbers or decimals.

Reduce Order Qty by Cancel Amount

When set to Y, the cancellation logic will reduce the quantity ordered by the quantity cancelled when line-item cancellations occur.

Note: Many EDI accounts want to see the actual quantity ordered. If an order ships short, then they can explain the shortage from the cancelled lines that appear and from line-items containing a partial shipment. Reporting back a different quantity ordered than what was imported into Synapse would usually yield an exception. This setting overrides the Default Value “REDUCEORDERQTYBYCANCEL”.

Additional Contacts

These fields allow the entry of 5 additional contact name, phone, email, and fax information.

Customer Logo

This allows a bitmap logo to be attached to the customer. It can be used for reports. Right click to load the logo.

Default Order Attachment Directory

Used as the default directory when orders with attachments are added via EDI. The default value is ATTACHDIRPATH. The attachment file (whose prefix is the customer’s reference number for the order) is automatically transferred into this directory.

Additional Buttons



- Creates a copy of the customer settings in a specified database. You can enter a new customer ID to copy a customer to a new customer.



- Accesses the Rate Maintenance screen.



- Accesses the Product Group Maintenance screen.



- Accesses the Item Maintenance screen.

Customer/Receiving

Customer/Receiving/Options

The screenshot shows the 'Customer INA-The Food Countess' software interface. The main menu bar includes 'Name', 'Receiving', 'Shipping', 'Billing', 'Dictionary', 'Labeling', 'Facility Settings', 'Handling', and 'Trading Partners'. Below the menu is a toolbar with various icons. The 'Receiving' tab is selected. The main area is titled 'Item Info Required Upon Receipt'. It contains several sections for capturing item information:

- Lot #:** A dropdown menu set to 'Not Required'. To its right are 'Min Seq:' and 'Max Seq:' input fields.
- Serial #:** A dropdown menu set to 'No'. To its right are 'Min Seq:' and 'Max Seq:' input fields.
- Color:** A dropdown menu set to 'Yes'. To its right are 'Min Seq:' and 'Max Seq:' input fields.
- User 2:** A dropdown menu set to 'No'. To its right are 'Min Seq:' and 'Max Seq:' input fields.
- User 3:** A dropdown menu set to 'No'. To its right are 'Min Seq:' and 'Max Seq:' input fields.
- Manufacturing Date:** Two radio button options: 'Yes' (selected) and 'No'.
- Expiration Date:** Two radio button options: 'Yes' (selected) and 'No'.
- Country Of Origin:** Two radio button options: 'Yes' (selected) and 'No'.

To the right of these sections are columns for 'Add'l Capture', 'RF Screen Label', 'Format Validation', and 'Parse Field Entry' settings. The 'Format Validation' section includes 'Specified', 'Default', 'Rule', and 'Action' fields, with 'Lot' specified and 'Warn' as the action. The 'Parse Field Entry' section includes 'ASN Capture Line Number', 'Verify Sale Life', 'Reuse LP's', 'Reuse Shipped XP's', 'Auto Assign Inbound Loads', and 'Entry Field' set to 'None'.

At the bottom left of the window, a status message reads: 'LINUX2TEST Facility ZET (Last Update by ANN at 10/24/2013 09:21 AM)'.

Item Info Required Upon Receipt

Lot

The following options are available:

- Yes – Lot number must be recorded for inbound inventory.
- AutoSeq – Lot number is automatically assigned to inbound inventory. A minimum and maximum number can be entered.
- Also Outbound – Lot number must be recorded for both inbound and outbound inventory.
- Some Outbound – Lot number may be optionally entered on outbound orders.

- Upon Pick – Lot number must be recorded during picking.
- Not Required – No lot number tracking is performed.

Lot number options and associated processing are described in the table below:

Option	Definition	Lot ID Required for Inbound Order Entry	Lot ID Must be Entered During Receiving	Lot ID Required for Outbound Order Entry	Lot ID Must be Entered During Outbound Shipping
N – Not Required	No lot # tracking is performed	No	No	No	No
O – Also Outbound	Lot # must be recorded for both inbound and outbound orders	Yes	Yes	Yes	No
P – Upon Pick	Lot # must be recorded at pick	No	No	No	Yes
S – Some Outbound	Lot # can be recorded for outbound order	Yes	Yes	Optional	No
Y – Upon Receipt A - AutoSeq	Lot # must be recorded upon receipt	Yes	Yes	No	No

Serial

- Yes – Serial number must be recorded for inbound inventory.
- AutoSeq – Serial number is automatically assigned to inbound inventory. A minimum and maximum number can be entered.
- No – No serial number tracking is performed.
- Upon Pick – Serial number must be recorded during picking.

User 1, User 2, User 3

User 1, 2 and 3 fields contain information that is based on customer and item requirements. For example, if a manufacturer of paint requires the capture of a color code, one of the user-defined fields can be designated for this purpose. RF-screen Display Labels and CRT-screen Labels can be defined to more clearly present the meaning of the user-defined fields.

- Yes – User field value must be recorded for inbound inventory.
- AutoSeq – User field is automatically assigned to inbound inventory. A minimum and maximum number can be entered.
- No – No User field value tracking is performed.
- Upon Pick – User field value must be recorded during picking.

Note: There is an RF limit of 14 characters for User 1 and User 2. The RF limit for User 3 is 19 characters.

Special Processing for User 2

Location Load (option 91) and Plate Inquiry (option 92) do not process User 2 values.

Special Processing for User 3

The following functions display only the first character of the RF tag (regardless of what was entered in the CRT) and allow for a 19-character entry or display with no space after the prompt:

- 1-Step Receipt - option 11
- Detail Return - option 18
- Inv Adjustment - option 81
- Location Load - option 91
- All types of "Picking"
- Can't Pick
- Shipping Audit - option 49
- Plate Inquiry - option 92
- Kitting – option 61
- Dekitting – option 64

User 3 can also be used as a free form text field to record temperatures or other miscellaneous data for individual lips. This option is only available when the No option is set for User 3 and is used by limited installations.

Manufacturing Date

- Yes – Manufacturing date must be recorded for inbound inventory.
- No – Manufacturing date is not required for inbound inventory.

Expiration Date

- Yes – Expiration date must be recorded for inbound inventory.
- No – Expiration date is not required for inbound inventory.

Country of Origin

- Yes – Country of Origin must be recorded for inbound inventory.
- No – Country of Origin is not required for inbound inventory.

Note: In order to accommodate a 19-character input area for User 3 in Location Load, Country of Origin is not captured.

Auto Sequencing Notes

Auto-sequencing is a feature that allows the assignment of user defined number sequences for Lot Numbers, Serial Numbers and User 1, 2 and 3 in 1-Step Receiving and CRT Receiving (Receive Load). When this is set for a field, license plates created for items will have a value automatically entered into the field.

1. This function is **not** available for Location Load and Location Fill.
2. Multiple Plates received for the same item in the order, should have the same sequence number even if receiving is interrupted and started again later.
3. The sequence numbers can be overridden as part of the receiving process.
4. Format Validation and Parse Rules should not be used in conjunction with this feature.
5. The Manufacture Date, Expiration Date, and Country of Origin fields are not included in this feature.
6. The number placed in the field will be pulled from a normal Oracle sequence and should be at least 6 digits long. The value loaded into the license plate will be padded with leading zeros to make the length of the minimum and maximum values equal. For example if the min = 1 and the max = 100000, the numbers generated will be 000001, 000002, etc.
7. The maximum value that can be used is 999,999,999.
8. If the maximum is reached, the Oracle counter will restart at the minimum value.
9. Item level sequences will override customer level sequences.
10. For Lot processing, AutoSeq is the same as selecting Y-Upon Receipt, except that minimum and maximum sequence numbers are required for auto-sequencing.
11. For serial number, User 1, 2 and 3, the Synapse processing after the plate is created will be the same as the Y option.

Add'l Capture

ASN Capture

ASN Capture Radio Buttons are available for Serial #, User 1, User 2 and User 3 with 2 options; Yes and No.

If an option is Yes, this information will not be recorded on the LP but in separate ASN capture tables. These tables will then be checked at picking to verify that inventory with the appropriate serial # or user-defined field had been received.

This option needs to be set prior to any inventory being received. If inventory currently exists when this option is activated, that inventory will not be allocated for outbound orders.

Note: This processing is not to be confused with receipts that are EDI transmitted via ASN transactions to simplify receiving via the RF ASN Receiving option 12.

1-Step Receiving with ASN Capture

When executing the 1-Step Receipt function for items that require ASN capture, note the following:

1. If any item has both required and ASN capture set for a field (serial number or user items 1 thru 3), the required option takes precedence and ASN capture is ignored.
2. After all non-ASN capture data has been entered for a plate, the prompts for the ASN capture fields are displayed beneath the existing data and the operator then repeatedly enters the ASN capture data. These are the only enterable fields.
3. The data is not stored in the plate but is saved in another table. The operator may exit entry of the ASN capture fields early and the plate will be updated accordingly.

ASN Capture Duplicate Checking

The following rules are used for duplicate checking when ASN capture data is being entered. There must be a format validation rule for the item and the rule must not allow for duplicates.

1. If an unshipped shipping plate exists – prohibit
2. If an inventory LP exists (returns plate) – prohibit
3. If there is receipt history for the same receipt order – prohibit
4. If there is receipt history for a different receipt - warning

ASN Capture Duplicate Checking with Do qty 1 LPs

ASN capture can also be mixed with "Do qty 1 LPs?" processing. There must be a format validation rule for the item and the rule must not allow for duplicates. When executing picking functions for items that require ASN capture, note the following:

1. If unshipped shipping plate exists – prohibit
2. If inventory LP exists (returns plate) – prohibit
3. There will be a warning message if the value was never received

ASN Capture Line Number

Allows the processing of line numbers for specific EDI receiving transactions. It is independent from the ASN Capture processing outlined in the above paragraphs.

Verify Sale Life

The Verify Sales Life function allows you to automatically place stock on hold upon receipt if it is going to expire within a specified number of days.

For example, if an item you are receiving is going to expire in 5 days you may not want to make it available for shipping. By the time you process it through the warehouse, ship it and the consignee receives it, the product may already have reached its expiration date. If you set the minimum sales life to 10 days, when items that expire in less than 10 days are received, they will automatically be placed in Vendor Compliance (VC) status and won't be available for shipping.

To use this function, the Verify Sale Life check box must be checked, the Min Sale Life Days on the Item Specs Specs tab must be entered and the expiration date must be set to Yes for the item on the Item Specs Receiving Options -1 tab.

Reuse LP's and Reuse Shipped XP's

When these boxes are checked the system allows the receipt of license plates that are on record and have been used in the past. This option is limited to RF receiving. Checking the Reuse LP box allows the reuse of deleted LiPs, selecting the second checkbox allows the reuse of XP's (cross-reference plates) which have been shipped.

Even though there are two options, if both are checked the RF operator will only be asked the question once per receipt. If a deleted plate is entered first they will be asked "LP used. Reuse?" and if a shipped XP is entered first they will be asked "XP shipped, Reuse?". When a shipped XP is reused, there will be an informational message logged under author REUSE_XP containing both the XP and the associated shipping plate. License plates will only be able to be reused within a single customer; they cannot cross customers, even if both customers are configured for license plate reuse.

This processing is not related to reusable "TO"TE plates.

Auto Assign Inbound Loads

This allows inbound EDI orders to be released from HOLD and placed into PLANNED status and assigned to a load. The Carrier must be imported on the EDI for this process to work correctly.

RF Screen Label

The RF display label can be entered for Lot #, Serial #, User 1, 2 or 3. If no screen label is specified, the default value will be displayed on the RF screen. Only the first character displays for User 3. Note: There is special processing for User 3 if a 19-character input field is used.

Special 20 Character Entry Setup

1-Step Receipt (option 11) allows the entry of a 20 character User 3. If the RF Screen Label for User 3 begins with a plus sign (+) then the entire width of the RF screen (20 characters) is available up for data entry. If there is available space on the screen, the line immediately above will contain a prompt surrounded by dashes (<--- ... --->) where ... is replaced with the final 4 characters of the RF Screen Label for User 3 – if there are no characters then UITM3 is used.

Format Validation

Rules

Format validation rules can be chosen for Lot #, Serial #, User 1, 2 or 3. These can be set so that the data is validated upon entry, i.e., accept only numeric characters, the entry must have 10 characters, etc. These rules are maintained via the Setup/Format Validation Rules Screen. See the User Manual Documentation for an explanation of the rules. CRT and RF entries are validated against these rules.

Actions

An Action is specified for each rule:

- Warn – Warns you that the data does not comply with the format validation for the field.
- Prohibit - Prohibits you from making an entry that does not comply with format validation for the field.


Parse Field Entry

The Purpose of the parse field entry is to scan a serial #, lot #, user 1, 2, or 3 and parse all or part of a value into another field. The original field value is kept in the scanned field. For example, the first 6 characters of the lot number is also the manufacturing date. By setting up the lot number as the input field and the manufacturing date as the parsed field, the entire lot value will be kept in the lot number field and the first 6 characters are extracted and put in the manufacturing date field. To set a rule:

- Double click on the Rule field and select a rule from a list. Note: The rules are created in Setup/Parsing Rules.
- Select the Entry Field for the rule from the pull down list.
- Set the Parse Rule Action Radio button to Yes.

See the Setup/Parse Rules in the User Manual Documentation for an explanation of the parse rules.

Customer/Receiving/Options 2



Receiver Report Format

This defines the directory path and name for the default receiver report (Crystal report) for this customer. This overrides the default value set for RECEIVERREPORT.

Line Number Options

Verify by Line Number

This is used for EDI processing. Select this entry to indicate the Customer's Receipt Orders contain multiple line number entries for each Receipt Order Item. Synapse will sort the line number entries by DTLPASSTHRUDATE01 (usually this would be defined in the order import as the expected receipt date of a delivery schedule) and Line Number to determine the expected receipt quantity. This is used in Blanket PO Processing.

Line Number Processing

This is used for EDI processing and if selected, the system stores a breakdown of line numbers for each expected item/lot. The DTLPASSTHRUNUM10 field must contain the line number upon import.

None

Line numbers are not tracked.

Variance %

This entry represents an acceptable variance for the receipt's line number quantity. Over-receipt warnings are not generated unless the over-receipt exceeds the expected quantity and the variance value. Enter a whole percentage value (e.g. Ten percent is 10). This is used in Blanket PO Processing in conjunction with the Verify by Line Number option.

Quality Assurance

This section of the screen sets the rules for the customer for Quality Assurance (QA) processing. Quality Assurance processing allows inventory from receipt orders to be routed through an inspection process as part of the receiving process. The results from the inspection can be entered via CRT or RF processes.

QA Request Entry Allowed

Check this box to enable the QA functionality.

QA Hold Receipt Open

Check this box if the receipt cannot be closed until all inspections have been completed.

Note: If the original PO is to be used for future receipts, this box should not be enabled. This box is for one-time POs only, not recurring POs.

Enforce Sample Size

This allows the enforcement of the QA sample size. An inspection cannot be closed if the number inspected is not greater than or equal to the calculated sample size.

Generate recurring requests by PO and item

Checking this box allows for recurring POs with the same Item to be given the same QA parameters and the initial PO and Item.

Note: The QA Hold Receipt Open and Generate Recurring Requests by PO and Item options cannot both be checked. This will create conflicting processing and a validation error will be displayed.

Single-Quantity License Plates

- Yes - All license plates will have a quantity of 1. This prevents you from creating a LiP in a quantity greater than 1 when receiving a product (via receiving, returns or inventory load) that requires data capture and specifies no duplicates. It also affects processing that allows the quantity of a LiP to be changed. This would most commonly be used for an item that requires unique serial numbers.
- No - License plates can have a quantity > 1

Note: If the item is set to a Max qty 1, then the unit of measure must be the base unit of measure.

RF screens that are affected by this setting include:

- Phys Inventory - option 36
- Location Load - option 91
- Work order - option 61
- Inv Adjustment - option 81
- Detail Return - option 18
- Damaged Items - option 96
- Cycle Count - option 35
- Build Pallet - option 13
- Dekitting – option 64
- 1-Step Receipt - option 11

CRT-based processing affected by this setting includes:

- Inventory Adjustment
- Receive Load
- Returns

Maximum Digits in RF Quantity

The MAXRFQTYLENGTH is set on the setup/default values screen. If nothing is set, the system defaults to 4. The Maximum Digits in RF Quantity can be set for each customer and overrides the system default values.

1. If 7 digits are entered, the 7th digit may end up adjacent to the UOM tag on the RF Screen, e.g., QTY 1234567UOM _____. This will not affect the entry or processing of the 7-digit value.
2. If a value is entered that is longer than the current limit, the current limit rules are used to change that value. For example, if a LiP has a quantity of 100,000, but the limit is now 4 digits, an operator can only enter a top value of 9,999. If the operator wanted to enter the value of 100,001, the limit would need to be changed before the operator could enter the data.

This logic is limited to the screens listed below:

- Location Load - option 91. If the final value is 0, Location Load is disabled - the RF operator can still access the function but they cannot get passed entering the customer.
- 1-Step Receipt - option 11
- Putaway – option 32
- Damaged Items - option 96
- Inv Adjustment - option 81
- Phys Inventory - option 36
- Movement – option 33

- Cycle Count - option 35
- Depick - option 72
- Depick by LIP – option 48

Note: Because the customer ID is not known when these transactions are started, the screens initially allow for a 7-digit quantity. After the customer has been verified and the length limit is calculated, the actual entered length is checked and any appropriate error message is displayed.

Default Weight UOM

This determines which weight unit of measure - lbs or kgs - are displayed or expected in various Synapse and RF screens.

Capture Pick UOM

This allows the Serial Number Capture/Tracking to be by pick unit of measure, not the base unit of measure. For example, if the base unit of measure is each and the pick uom is case, the serial number is tracked for the case. The serial number is available for the picked UOM to be a part of the 945 & 856 output for those EDI transaction sets as required.

Do NOT allow receipt of damaged product

If this option is selected, LP's cannot have a DM - Damaged Inventory status at receipt.

Allow Receipt Cloning

When activated, this option allows you to copy a receipt order for this customer. If the box is not activated, the feature is disabled for this customer. The cloned receipt retains the same order ID but is assigned a new ship ID.

Master Receipt Limit

When this option is activated it allows the customer to use the Master PO receipt limit processing. The sum of received inventory on the child receipts cannot exceed the master receipt totals. The master limit can only be overridden by special security authorized user.

Track Trailer Temperatures

When activated, this will require the capture of trailer temperatures on inbound receipt loads. When managing inventory for clients with temperature controlled product, it is a common practice to record the temperature of the trailer when product is received.

Use Catch Weight

This setting determines whether catch weights apply to all items for the customer. The values are:

- Yes – All items for the customer have catch weights.
- No – Items do not have catch weights.

Outbound Catch Weight

This parameter determines the type of outbound catch weight captured for all items for the customer. The options are:

- Blank - No outbound capture is required.
- G – Gross weight entry is required.
- N – Net weight entry is required.

If Use Catch Weight is set to No (or blank), then Outbound Catch Weight is ignored.

Lbs to Kgs Conversion Factor

You can enter a factor for converting pounds to kilograms for a customer.

A system-wide default can be established through Setup/Standard UOM Conversion. Enter LBS in the From field, KGS in the To field and a conversion factor in the Quantity field.

If neither of these factors is entered, the system defaults to a conversion factor of 2.20462262.

Rounding

The option of rounding the result of a lbs to kgs conversion is configurable. A rounding option of:

- Yes - The standard mathematical rounding rules based on 8 decimal places are followed.
- No - Truncates the resulting weight to 8 decimal places.

A system-wide default can be established in the default values table by creating an entry called WEIGHT_ROUNDING and setting the value to either N or Y.

If both of these values are absent, the system will default to No rounding.

Putaway Highest Whole UOM

When you receive an item you specify the unit of measure (UOM) you are receiving and normally this is the UOM that the putaway process uses when scanning the Putaway Profiles. If this flag is set, then the putaway process converts the base UOM and quantity to the highest whole UOM for the item. The highest whole UOM is then used to scan the Putaway Profiles. For example, if this option is selected, if you receive 100 cases of an item and there are 100 cases on a pallet (highest whole UOM), then the pallet UOM will be used to search the Putaway Profiles and find a warehouse location.

Allow Line Item Weights

This setting gives you the flexibility to enter the catch weight of an entire shipment by item/lot at order entry then have the system calculate the catch weight per plate. The RF operator still has the ability to change the information if needed. When this functionality is used the system will calculate the average weight of the pallet and the RF user will not be prompted for weight on each plate created.

Track inventory status adjustments for open receipts/returns

Check this box if you want to track inventory status changes for stock that is on open receipts or returns. For example, if stock is received on QA status and it changes to AV status prior to the receipt being closed, checking this box allows you to track this status change.


Carry Over Unreceived Expected Quantities

On a receipt order, if the expected quantity for any given line is not received, the balance will be carried over to another order record that is created automatically by the system. The auto-created order will have the same Order ID but a new Ship ID. All header fields will be duplicated on the auto-created orders. In the case of orders for which line number processing is in use, when receiving occurs, quantities received will be applied against the various sub-lines in the normal manner. Canceling an order will stop the process. So, if the initial order is canceled, no order auto-creation will occur for that order. Cancellation of an auto-created order will similarly stop the process.

Prefill Putaway Location

If this option is checked, the Location Verify Loc or At field will automatically be filled with the destination location selected by the system (appearing in the Location field) on the RF. The prefilled location can be changed by the RF operator. If NO SPACE is selected by the system, nothing will be prefilled. Prefilling will occur for any putaway task whether the putaway is Task driven, 1-Step Receiving or requested on the Putaway LP screen.

Customer/Receiving/Confirmation



Cust PO - Confirmation Types

Hard Copy

Click the Hard Copy check box to print a PO confirmation report.

Hard Copy Report Format

This field defines the directory path and name for the default PO confirmation report (Crystal report) for this customer. This overrides the default value set for POCONFIRMATIONREPORT. At Load Close the system will print the report pointed to by the DAMAGEREPORT parameter in the default values table in addition to the POCONFIRMATIONREPORT if applicable.

E-mail

Click the E-mail check box to e-mail a PO confirmation report. The e-mail is sent at Load Close for the receipt. To resend the report, click the Reprint PO Confirmation Button on the order screen.

E-mail Report Format

This field defines the directory path and name for the Crystal report e-mail version PO confirmation for this customer.

E-mail Address

Enter the e-mail address to which you want to send the PO confirmation report. If the E-mail box is checked, this e-mail address will be used first. If the e-mail address is blank, the Customer/Billing/Addresses/Receipt tab is checked for an address. If no e-mail address exists, the Customer/Name tab e-mail entry is used.

EDI – Mapping Format

Choose the Purchase Order confirmation EDI mapping format for this customer. These values are set up in the Import/Export Utility.

Include Cancelled Orders

If checked, the system will generate an Import/Export request upon cancellation of an Inbound Order (types R and Q).

Putaway Confirmation Method

This entry determines the RF entry information required on a multi-stop putaway.

- Location, Item, Quantity
- Location, Quantity

Seal Number Verification

Require Seal Number Verification

If checked, a seal number entry is required during RF receiving (options 11 and 12). This is used as part of the C-TPAT processing (Customs-Trade Partnership Against Terrorism).

Order Header Field that contains Seal Number

The pass-thru field for the Seal number to be matched is identified here.

Customer Email on Receipt Close

This function sends e-mails to customers when a receipt load is closed. Configurable options allow the e-mail to be adapted for the recipient. This configuration uses the Oracle e-mailing functionality used elsewhere in Synapse.

The Email Body will accept the following wildcards:

- %CARRIER% - carrier code from the load closed
- %CARRIERNAME% - full name of carrier from the load
- %TRAILER% - trailer number for the load closed
- %LOADBOL% - load Bill of Lading (BOL) number
- %SEAL% - seal from the load
- %PRO% - Pro from the load
- %CLOSEDDATE% - date load was closed in mm/dd/yyyy format
- %CLOSEDTIME% - time load was closed in 24hr:mm format.
- %REFERENCE% - reference from the order(s) associated with the load. If there are multiples, a comma separated list appears.
- %PO% - PO from the order(s) associated with the load.

Notes:

1. If there are multiples, a comma separated list appears.
2. When these options are configured for a carrier, an e-mail will be sent to the email address or addresses (comma separated lists will be supported in the To Address) specified when a load of the appropriate type is closed.
3. The list of wildcards for this function is less comprehensive than for some other e-mails so note the list above.

Notify on Receipt Close E-mail

Check this box if the customer requires a confirmation upon receipt load close.

From Address

Enter the e-mail address that will be sending the confirmation e-mail.

To Address

Enter the address that the confirmation will be sent to.

E-mail Body

Enter the text and wildcards that you want included in the confirmation e-mail.


Sample E-mail:

The screenshot shows an email message in plain text format. The message header includes 'From: support@zethcon.com', 'To: sally.winchell@zethcon.com', and 'Subject: Load Close Notification (Load #201184)'. The body of the message contains the following text:

This inbound shipment has been received::

order 369460
REFERENCE
PO
CARRIER 3WAY
CARRIER NAME 3WAY TRANSPORT
LOADTRAILER 12
LOADNO 201184
LOADSEAL
LOADPRONUMBER
CLOSEDDATE 09-may-2012
CLOSEDTIME 13:20

Customer/Receiving/Instructions



This screen provides a free-form text area for adding customer-specific receiving instructions to be shown on the RF terminal at receiving.


In most installations, the RF display screen is limited to a width of approximately 20 characters. The following rules apply for display of the free-form text area entered via the CRT on the RF displays:

1. A word (contiguous sequence of non-blank characters) will not be split across multiple lines unless the word is longer than the width of the screen.
2. All blanks at the beginning of a line (i.e. left edge of the screen) are removed.
3. All non-printable characters (e.g. carriage return, tab) are replaced by a single blank.
4. Any contiguous sequence of blanks is replaced by a single blank.

Automatically display instructions when handling

If ‘Automatically display instructions when handling’ is checked, the instructions automatically display on the RF. If the box is not checked, the “*” displays and the RF operator can view the instructions by using a function key.

Customer/Receiving>Returns



This screen is used to enter the customer-specific return codes to be used when receiving returns. Facility-level restrictions are defined on the Facility Returns Disposition Tab.

RMA Required for Returns

If this box is checked, the customer requires a Return Merchandise Authorization (RMA) upon the receipt of each return. The RMA number will be entered on the Return Order.

Original Order Required

If this box is checked, the return must be tied to an original order ID. The order ID will be required when the Return Order is created.

Disposition

This is the category of the returned stock. These values are maintained in the ReturnsDisposition validation table.

Default Return Quantity

If this field is populated, the quantity field on the Edit>Returns/Return an Item tab will be pre-populated with this quantity after the receiving item is selected. This is useful for customers that have consistent return quantities.

Ignore Anniversary Date When Consolidating Returns Merchandise

When combining plates, all the data (item, lot, expiration date, etc.) must match. Select customers use anniversary date for billing purposes. If this is not used for this customer, checking this box will allow plates to be built with different anniversary dates.

Carry Over Unreceived Expected Quantities for Returns

On a return order, if the expected quantity for any given line is not received, the balance will be carried over to another order record that is created automatically by the system. The auto-created order will have the same Order ID but a new Ship ID. All header fields will be duplicated on the auto-created orders. In the case of orders for which line number processing is in use, when a partially received returns order is closed, any subline for which only part of the expected quantity was received will “carry over” the unreceived balance to the auto-created order. Any subline for which no quantity was received will carry over in full to the auto-created order. This will continue until all expected quantities have been received. You may still over receive against an order as you can currently. Canceling an order will stop the process. So, if the initial order is canceled, no order auto-creation will occur for that order. Cancellation of an auto-created order will similarly stop the process.

Returns Reason Codes

Valid return reason codes, descriptions and abbreviations that are available when processing returns for the customer are entered here. These codes are used on the Edit/Returns/Return an Item tab.

Customer/Receiving/ABC Cycle

	Percent	Frequency	Counts This Month
A:	50	3	
B:	30	1	
C:	20	1	

Inventory Adjustment Export Format
Standard Inventory Adjustment 947

Warn Before Sending

LINUX2TEST Facility ZET (Last Update by ANN at 10/25/2013 10:01:30 AM)

This screen is used to set the customer-defined percentage of items that should fall in each velocity and the frequency (per month) that the item should be counted. Refer to the chapter in the SYNAPSE User manual for information about ABC Cycle Count processing.

Last Cycle Count Request

This is an information only date field and shows the date that the last cycle count was requested.

Percent

This field allows you to set the percentages of items of each velocity for the customer.

- A - velocity is for the fastest moving items
- B - velocity for the medium moving items
- C – velocity for the slow moving items

Frequency

This field defines the monthly frequency that the items should be counted.

Counts This Month

Displays the number of ABC cycle counts requested this month. See the documentation on ABC Cycle Counting for more information.

Additionally this screen identifies the following non-ABC counting options:


Inventory Adjustment Export Format

This drop down box allows a specific inventory adjustment export format to be specified for the customer.

Warn Before Sending


When this option is checked, a “Send EDI Adjustment Advice” confirmation message appears on the CRT when an inventory adjustment is made. If you respond Yes, the export will be queued to occur. If No, it will not. RF inventory transactions are not affected by this option.

Customer/Receiving/Suppliers



Customers are linked with Suppliers on this screen. This information is used when entering inbound orders. The supplier information must first be entered on the Setup/Supplier Maintenance screen.

Customer/Receiving/Facility Returns Disposition



Facility

This information is set up by facility. The CRT operator must be in the Facility when adding or editing these entries.


Disposition

This is the category for returns. This data is maintained in the 'ReturnsDisposition' validation table.

Sortation Location

This defines a valid location in the facility where returns for the specified disposition are sent for further processing.

Customer/Receiving/Overage



The Receiving/Overage Tab allows you to define the acceptable overage amount - by quantity and/or dollar amount - for a customer. This option is designed for RF receiving only.

During the receiving process, the quantity entered is checked against the quantity already received to determine if the entry exceeds the allowed limit. Note: If the percent option is selected, no new items are allowed to be received (since the entered quantity on the receipt would be 0 for a new item, then any percent of 0 = 0).

There are separate parameters for receipts and return receipts.

Units

The available options are:

- None (disable)
- Amount (unit quantity)
- Percent (units)

Dollars

The available options are:

- None (disable)
- Amount (dollar amount)

- Percent (dollar amount)

Amt 1 and Amt 2

Indicate which amount in the Item Maintenance/UOM Tab to use for the Dollars calculation.

Supervisor Override Code

A Supervisor Override Code can be entered to allow you to override the set overage receipt limit. The Supervisor Override Code will be required during RF receiving for the overage to be accepted.

Customer/Receiving/Inventory Status Change

From Status	To Status	Location Type	Adj Reason	Task Types	Last User	Last Update
QA	AV	STO	QA	PA	ANN	10/25/2013 11:46:09

This tab defines criteria to automatically generate an inventory status change on an RF plate drop. When the plate is dropped to a location that meets the criteria, an inventory adjustment is made to change the inventory status on the plate.

This process was designed for instances where the inventory is received on hold status and adjusts to available status when it is put away in a storage location

From Status

This is the original inventory status prior to the adjustment. It must be a valid inventory status and is a required field for using this function.

To Status

This is the inventory status for the adjustment. It must be a valid inventory status and is a required field for using this function.

Location Type

This is the location type that will initiate the inventory adjustment. The adjustment occurs when the plate is dropped into this location. This is a required field for using this function.

Adj Reason


Enter the Inventory Adjustment reason. This data is maintained in the ‘AdjustmentReasons’ validation table. It is a required field for using this function.

Task Types

Enter the RF task type or types that will initiate the adjustment. This data is maintained in the ‘TaskType’ validation table. It is a required field for using this function.

Customer/Shipping

Customer/Shipping/Options-1



Default Backorder Policy

This defines the Default Backorder policy for this customer. This can be overridden at the item and order-line levels. For Small Package Orders, see the chart under the “Auto Short Ship Small Package Orders” later in this section. Valid Back Order Status Codes:

Value	Normal Processing	Abbreviation
A	Backorder the entire line item – Do not pick the line short. This option cancels the line item at wave release and creates a new order with the exact same line item.	BackOrderAll
N	No Backorder - Ship Short - No backorder is created at load close.	NoBackOrder
P	Ship Available- Backorder is created for the shortage at load close	BackOrdrPart
W	Await CSR – Works in conjunction with the Backorder CSR Email option. When a shortage occurs at wave release, processing will stop for the order, an internal flag will be set for the order and any tasks created will be deleted. A Ship Short button will appear on the order. When clicked, the order will process as if the “N” (No Backorder) policy is in effect.	AwaitCSR
X	Cancel the line item at wave release.	Cancel

These values work in coordination with the “Reject short orders and allow resubmission” check box on the Customer/Shipping/ Options – 2 screen. If this box is checked, a short order is cancelled upon commitment, regardless of the back order policy of any of the line items.

This processing is slightly altered for Material Issue generated orders. See additional documentation associated with this process.

Backorder CSR E-Mail

This is used in conjunction with the “W” (AwaitCSR) backorder option to identify and e-mail the CSR to communicate that order(s) need to be reviewed.

Allow Substitutions

This radio button allows item substitution processing to be turned off or on at the customer level. Item substitutes are defined at the item level on the Item Maintenance/Substitutes screen.

Default Inventory Status Selection

This data is required for the addition of a new customer. The customer-level default inventory status code (it can be single or multiple status codes) for inventory that is allowed to be shipped is set here. These values are set up in the InventoryStatus validation table.

Default Inventory Class Selection

This data is required for the addition of a new customer. The customer-level default inventory class code (it can be single or multiple class codes) for inventory that is allowed to be shipped is set here. These values are set up in the InventoryClass validation table.

In order to associate a list of valid Inventory Class values with a customer, there **must** be a validation table named “class_to_company_ZZZ” where the suffix (ZZZ) is the Customer ID. Otherwise, the available values for inventory class selection default to the InventoryClass validation table.

If “class_to_company_ZZZ” is setup, and the customer ID is entered on the following screens, the criteria selection will be restricted to the values valid for the customer.

- Lookup/License Plate Information
- Lookup/Shipping Plate Information
- Inventory Class lookup,
- Return Order Lookup

Additionally, the Item/Shipping/Options1 screen will restrict the choice of Default Inventory Class Selection based on the “class_to_company_ZZZ” table.

See the section in this manual on Miscellaneous Setup Topics for additional information.

Shipment Order Quantity Type

System supported values are:

- Exact – The system will attempt to fill the order with the exact amount ordered. This is normally for all items ordered by a defined unit of measure, such as case or each.
- Approximate – The system will attempt to fill the order within the % variance entered in the Acceptable Pick Range field. This is usually for items ordered by weight such as raw materials.

Acceptable Pick Range (% of Ordered)

Default values for approximate quantity types (see above).

- Minimum
- Maximum

Weight Check Required

- Yes – Manual weight checking is required prior to order loading.
- No – Manual weight checking is not required.

LiP Substitution Reason Required

- Yes – During picking, if a LP is specified and substituted, the RF operator must enter the LiP Substitution reason. The operator uses a process similar to the “Can’t Pick” in picking and the reason codes available are from the “CantPickReasons” validation table. The RF operator must use the F6 key to enter the reason code when substituting.

- No – Lip Substitution Reason is not required.

Auto Short Ship Small Package Orders

This setting works in conjunction with the Default Backorder Policy (discussed earlier in this section) for Small Package orders to allow for automatic short shipments and backorder creation.

Default Backorder Policy	Auto Short Ship Small Package Orders	Small Package Order	Results for Backorder
N – NoBackOrder X - Cancel	Yes – No Back Order Yes – With Back Order No	All Conditions	No Backorders Created – This setting will take precedence over the Small Package Setting
P – BackOrderPart A - BackOrderAll	Yes – With Back Order	Partial Quantity Available for line item	Partial Quantity shipped; Backorder Created for inventory not shipped – one backorder is created for the order
P – BackOrderPart A - BackOrderAll	Yes – With Back Order	Zero Quantity Available for line item – part of a multi-line order that shipped	Backorder Created for inventory not shipped – in this case the full amount – one backorder is created for the order
P – BackOrderPart A - BackOrderAll	Yes – No Back Order	Partial Quantity Available for line item	Partial Quantity shipped; No Backorder Created for inventory not shipped
P – BackOrderPart A - BackOrderAll	Yes – No Back Order	Zero Quantity Available for line item – part of a multi-line order that shipped	Order Line Cancelled at Wave release/No Backorder Created
P – BackOrderPart A - BackOrderAll	No	Zero quantity available for item	Backorder created at wave release
P – BackOrderPart A - BackOrderAll	No	Partial quantity available for item	No shipment, backorder created at wave release

Allow Order Changes During Picking

Allows outbound orders to be updated while:

- Released
- Picking
- Picked

If this is checked, orders that are in loading or loaded status can be updated using the Multi-Order editor.

See the separate documentation on this process. Processing is not available for Aggregate Inventory Customers.

FIFO Processing

This setting determines the FIFO window the operator can use to override a suggested pick.

- Enabled - When this is selected, a value needs to be set in the FIFO Window Days field. Strict enforcement – The operator will not be allowed to pick inventory outside of the FIFO date. Requests for alternate picks will only be created with inventory for the FIFO date.
- Disabled - When this is selected, no FIFO is enforced. When an operator picks an item allocated by FIFO, he will be allowed to override the pick or request an alternate pick for any allowable inventory for the item.

FIFO Window Days

Valid values are 1 –999. When the operator overrides a pick or requests an alternate pick, this value represents the number of days the system will allow the alternate inventory FIFO date to be in relation to the FIFO date of the inventory in the original pick.

This logic is also in effect for LIFO.


Estimate Cartons

This enables the functionality that populates the fields in the order header for Estimated Cartons and Estimated Cube.

Load Plate on Label Print

This enables the functionality that sets the order status to Loaded and prints a packing list when the last carton is scanned like small package processing.

Allow Shipment Split

This option allows outbound shipments to be split. On the Order Screen, the  button is illuminated when the feature is activated for the customer and you have security to perform the function. The order cannot be beyond committed status or assigned to a load. See User Manual documentation on this process. This processing is not available for Aggregate Inventory Customers.

Order Check Required

- Yes – Manual or RF order checking is required prior to order loading.

- No – Order checking is not required.

Default Bill Freight To:

A consignee can be entered here for the default bill freight ID on outbound orders. This value can be overridden at order entry. The consignee information must first be entered on the Setup/Consignee Maintenance screen.

Miscellaneous Shipping Requirements**Require Short Shipment Reason**

When this box is checked, you are required to enter a code that best describes the reason for the short shipment at the order detail item level prior to performing the load closing function. The reason code values are maintained in the ShipShortReasons Validation Table. The purpose is for documentation and reporting.

Require Late Shipment Reason

When this box is checked, you are required to select a reason that best describes the circumstances if the load close is past the allowable time variance based on the load appointment date/time. The reason code values are maintained in the LateShipReasons Validation Table. The purpose is for documentation and reporting.

Allowable Time Variance

Used in conjunction with the Require Late Shipment Reason box, this is the amount of time in minutes allowed after the appointment date and time on the load before a load close requires the entry of the reason code.

Order by Lot

This option allows order entry for customers that only deal in lot numbers. When checked, this functionality is enabled for all items for this customer.

When entering an outbound order, the cursor will automatically be focused on the lot field, skipping the item field entirely. When the user enters a lot number in the lot field and then tabs or clicks away from the field, the item number that matches the lot will be populated in the ordered item field automatically.

If two or more items exist in the customer's inventory for the entered lot number, the user will receive an error and will have to specify the item number. If no inventory exists for a lot number entered, the user will receive an error that the lot was not found. They will not be able to continue with the order. This would be similar to entering an item that does not exist for the customer.

XDock Processing

This setting is used to control the type of Cross Docking processing for this customer.

- A - All XDock Processing – The system will only create cross-dock picking tasks – no picking tasks are created from storage.
- N - No XDock Processing – The system will not create any cross-dock picking tasks.
- S - Standard XDock Processing – The system default, the system creates cross-dock picking tasks when required, otherwise tasks are created from storage.

See the User Manual documentation for more information on this topic.

Consignees

Customers are linked with Consignees on this sub-screen. This information is used when entering outbound orders. The consignee information must first be entered on the Setup/Consignee Maintenance screen.

Automatic Pro Number Assignment

This configuration supports the customer-level data needed for Automatic Pro Number Assignment.

Consolidate Orders By:

When assigning Pro Numbers to consolidated orders, the system will use the field specified here to determine which Synapse orders are auto-assigned the same Pro Number.


Carriers

An entry in this new grid will cause the auto-assignment to take place for outbound orders associated with the customer and carrier. The grid contains the following data elements:

1. Carrier – The carrier ID value from the Carrier table.
2. Event – The event that will trigger the auto-assignment. The events are:
 - Load Close
 - Wave Release

Note: If after automatic assignment, the system determines that the available unused Pro Numbers for a carrier is less than the minimum specified for that carrier, a warning message will be displayed.

Customer/Shipping/Options-2



Wave Template for Imported Orders

Wave templates that are used regularly are created and maintained using the Requests/Update Requests/Wave Planning Screen. The default Wave Template for Imported (EDI) orders should be set here.

Additionally, when manually releasing an outbound order from hold, if the release is successful (no validation errors) the system will check to see if a "Wave Template for Imported Order" value has been specified. If so, the system will automatically attempt to:

1. Commit the order.
2. Assign the order to a "Committed" Wave matching this template value using the same logic that already applies to imported orders. If a wave's order count limit is reached, its status is set to "Ready" and another "Committed" wave is created.

Reject short orders and allow resubmission

If this box is checked, the system will cancel any order that does not commit at 100% of its ordered quantity. If a "Wave Template for Imported Orders" has also been specified, the cancellation will take place when the order is imported into the system (since automatic commitment will occur at this time). Any short orders processed via Wave Planning will automatically cancel during the commitment process.

If this box is checked, the information for any cancelled order will be replaced in its entirety if the same "reference" number is re-imported into the system. If a re-import of a non-cancelled order is attempted, the system will reject the re-import request. So, setting this option enforces unique reference numbers. If this box is not checked, then duplicate "reference" numbers on customer orders are allowed.

This processing was designed for accounts where short shipments on orders are not acceptable. Since imported orders for these types of accounts are committed upon import:

1. If the order commits at 100%, then the system sends out an order confirmation and allows the order to be processed (i.e. picked and shipped).
2. If the order commits at less than 100%, then the system cancels the order and sends out a reject notification. The order may then be resubmitted with the same reference number in some future import.

Note: Synapse-initiated line cancels are not allowed on committed orders for accounts configured this way due to the fact that an order confirmation has already been sent.

Line Number Processing

If this box is checked, the system will track ordered item information at a line-number level. Synapse requires a unique item/lot combination to be entered for each line item on an order. Some customers send order-item information at a line number level subordinate to the item/lot level. If this box is checked, the system expects the "dtlpasstrunum10" column on the "orderdtl" table to contain a line number to uniquely identify a line-number/item/lot ordered quantity. The system will accumulate the different line-number combinations and the Order-Item Screen will reflect the total of all line-number quantities for the ordered item/lot value. If this box is not checked, the system will track the ordered items at the item/lot level. No line number information will be maintained.

Pick by Line Number

This option supports picking specifications by unit of measure (UOM) to be imported from the customer import file for an order. It is used in conjunction with the production of specific SSCC18 labeling. Contact the TSD at Zethcon for more information as this is not widely used.

Order Confirmation Export Format

Choose the order confirmation EDI mapping format for this customer if applicable. These formats must first be set up in the Import/Export Utility.

Reject Notification Format

Choose the order rejection EDI mapping format for this customer if applicable. These formats must first be set up in the Import/Export Utility.

CHEP Sender ID

Enter the customer's CHEP sender code. It is necessary if the customer uses the CHEP pallet tracking export.

Consolidated Waves Template Defaults

This feature allows outbound orders going to the same ship-to to be grouped into a “consolidated” order for planning, picking, packing and shipping purposes yet maintain the original order identity for tracking and reporting purposes.

If these fields are configured, the values will be transferred to the Consolidated Wave Box on the Wave/Options Tab at wave release.

Consolidate Orders

If this box is checked, outbound orders will be consolidated during wave release. If the Consolidate Orders box is not checked the following fields are not available.

Shipment Type

This is the shipment type of the orders that you want to consolidate. For example, you may want to consolidate all LTL orders.

Carrier

This is the carrier assigned to the orders you want to consolidate. For example, you may want to consolidate all the orders for the same ship-to that are being shipped on ABFS.

Service Level (if applicable for Carrier)

If the orders are multi-ship orders and a small package carrier is being used, you can enter a service level (Priority, 2-Day Ground) that you want to consolidate. The service level must already exist for the carrier.

Shipment Cost

Note that a shipment cost > 0 is required

See additional documentation for the Consolidated Order Processing option in Synapse.

Pallet Tracking Defaults

Based on these defaults, the pallet tracking tab of the load screen can be pre-filled if there is only one customer associated with the load.

Default Quantity

The default quantity is entered here. This must be greater than 0 for the Generate Default Quantities button  to be illuminated on the Load/Pallet Tracking Tab.

Default Pallet Type

Enter the default pallet type. This value must exist in the Pallet Types Validation Table.

Generate BOL Number

These settings are used in conjunction with special Crystal Report Bills of Lading (BOL) forms to generate/print BOL numbers based on these values. Options are:

- No – Do not generate a BOL number.
- Yes – By Ship To - A unique BOL number is generated per load/facility/ship-to.
- Yes – By Ship Terms/Postal Code - A unique BOL number is generated per load/facility/ship terms/5 digit postal code.
- Yes – By Customer/Ship To - A unique BOL number is generated per load/facility/customer/ship-to.
- Yes - By Customer/Ship Terms/Ship To - A unique BOL number is generated per load/facility/customer/terms/ship-to.

Assign Stop by Pass Thru

This feature supports load assignment from the following screens:

- Transportation Order Lookup
- Order Lookup
- Wave Release

Auto Assign Stop

Checking this box enables this feature.

Load Field

This field identifies the order header passthru field that contains the load assignment information.

Stop Field

This field identifies the order header passthru field that contains the stop assignment information. This is not used as the stop number but as the relative stop number during the assignment.

Allow mixed orders on outbound shipping plates

This field is normally checked. If there are customers where this is not an acceptable standard operational procedure, uncheck the box.

Track Outbound Trailer Temperatures

Checking this option will require the entry of temperature readings at the time of shipping. The operator will be asked to enter readings in three locations of the truck. The RF operators are then required to enter the temperatures on the RF and confirm them on the CRT.

Shipping Insurance

The value of all the items in the carton will be totaled and rounded up to the nearest \$100 when the Shipping Insurance option is selected. The field value will also be included in the MultiShip tables. This data is informational only. The Mutlishlistitem table will store the information at the item level. Included in this table will be the information for International shipments, including Shipping Insurance, Customs description, Country of Origin, HS Code and Selling Price

Calc Qty from Item on Catch Weight order by Weight

This checkbox, when checked, will cause the quantity to be calculated slightly differently than the standard calculation when an order is placed by weight against a catch weight item. In the standard calculation, Synapse determines the quantity for an order that is placed by weight for a catch weight item by dividing the weight ordered by the average weight in inventory. When this box is checked, the quantity ordered for a catch weight item ordered by weight will be calculated by dividing the ordered weight by the weight designated for the item in its setup at the unit of measure ordered.


Track Picked Pick Front Plates

Checking this option will allow the tracking of the lot numbers from not only pick fronts but also Totes and Multi-plates on the Shipping Plate.

Allow outbound order entry of minimum days to expiration

Checking this option will allow the items for this customer to use this process. See Setup/Customer/Item/Item Specs/Ship to Expiration Tab for more information on this process. If this is not checked, the Ship to Expiration Tab will not appear for the item.

Customer/Shipping/Options-3



Generate Pack List

The Yes/No radio buttons indicate if a pack list is to be generated for this customer. The Server radio button implies yes. This is used for the VICS BOL Server process.

Pack List Report Format

This field defines the directory path and name for the default pack list report (Crystal report) for this customer. This overrides the default value set for PACKLISTREPORT for the installation. See the Shipping/Pack List Tab to configure a pack list by carrier/delivery service code.

Generate After Audit

Checking this box allows the RF operator doing a RF Shipping Audit (Option 49) to print a packing list report for the carton just completed.

Generate Master Pack List

The Yes/No radio buttons indicate if a master pack list is to be generated for this customer. The Server radio button implies Yes. This is used for the VICS BOL Server process.

Master Pack List Report Format

This field defines the directory path and name for the default pack list report (Crystal report) for this customer. This overrides the default value set for MASTERPACKLISTREPORT for the installation. This is normally used for consolidated orders.

See the Shipping/Pack List Tab to configure a master pack list by carrier/delivery service code.

Bill of Lading Report Format

This field defines the directory path and name for the default Bill of Lading report (Crystal report) for this customer. This overrides the default value set for BOLREPORT for the installation. The system assumes that all automatically produced BOL's use the load ID as the input parameter for the Crystal Report.

Master Bill of Lading Report Format

This field defines the directory path and name for the default Master Bill of Lading report (Crystal report) for this customer. This overrides the default value set for MASTERBOLREPORT for the installation. The system assumes that all automatically produced BOL's use load id as the input parameter for the Crystal Report.

E-mail

If the E-mail box is checked, at Load Close, a Master Bill of Lading report and/or a Bill of Lading report are sent via E-mail to the Customer Accessorial E-mail address from the Billing/Addresses/Accessorial tab, or if that is blank to the Customer's E-mail address.

1. To resend the reports, click the Reprint BOL button on the Loads screen.
2. This functionality uses MAPI with Microsoft Exchange or Microsoft Outlook via Crystal Reports Server. The attached reports are in PDF format.
3. For BOL and Master BOL, the verbiage "The following orders were shipped on date/time" (date/time stamp from Load's last update) and the list of Reference numbers from the orders will be in the body of the email.

PDF

This option supports BOL production that includes an embedded driver signature. Please contact the TSD at Zethcon for additional information.

Preliminary Bill of Lading Report Format:

This field defines the directory path and name for the default Preliminary Bill of Lading report (Crystal report) for this customer. This is used for Aggregate Inventory customers.

Print at Wave Release

If checked, this will trigger the Preliminary BOL to be printed at wave release along with the Aggregate Inventory Picklist report.

Shipping Acknowledgement

EDI Mapping Format

Choose the shipping acknowledgement EDI mapping format for this customer. These values are set up in the Import/Export Utility.

Include Cancelled Orders

If this option is checked, the system will generate an Import/Export request upon cancellation of an Outbound Order (types 'O' and 'V').

Include Cross Cust Orders

If this option is checked, the system will generate an Import/Export request upon cancellation of a Cross Customer Order (type 'U').

Pallet Tracking Format

Used for the CHEP pallet export transaction. An entry in this field will cause the system to generate an export request upon the close of an outbound load. (Note that some customers do this reporting using a daily script and not for each load).

Freight Billing Export Format

Used to indicate a freight billing export is to occur when a load is closed or a small package order is shipped. Enter the export format.

Various EDI Formats

Shipping Summary Format

Choose the shipping summary EDI mapping format for this customer if applicable. These values are set up in the Import/Export Utility.

Stock Status Format:

Choose the stock status EDI mapping format for this customer if applicable. These values are set up in the Import/Export Utility.

Wave Release Acknowledgement Format:

When an order goes to released status from a lower status, this EDI export is produced.

Generate C of A Document

A Certificate of Analysis (COA) PDF document(s) and a cover-sheet style Crystal Report can be printed at Load Close. PDF documents are linked to customer/item/lot combinations by using the Edit/Certificate of Analysis screen.


- Yes – The system will attempt to print any COA reports at load close.
- Prompt – The system will prompt the CRT operator at load close to determine if report printing is needed.

- No – The system will not automatically print any COA reports.

C of A Shipping Report Format

Choose the Crystal Report that will be the Cover Sheet for the COA PDF. This report requires 4 parameters – order ID, ship ID, item and lot.

Customer/Shipping/Options-4



Aggregate Inventory Picking List Report Format:

This field defines the directory path and name for the default Picking List Report (Crystal report) for Aggregate Inventory customers. This overrides the default value set for PICKLISTREPORT for the installation.

E-mails

Consignee – Small Package and Non-Small Package

These options require the use of the Oracle Emailer. Please see Chapter 49 of the Synapse User Manual for additional information.

Small Package E-mail

If checked an E-mail will automatically be sent to the consignee's e-mail address when a small package is shipped. The consignee's E-mail is located on Setup/Consignee Maintenance/ Name.

Non-Small Package E-mail

If checked an E-mail will automatically be sent to the consignee's e-mail address when a non-small package is shipped. The consignee's Email is located on Setup/ Consignee Maintenance/ Name.

From Address:

The address the sent e-mail will appear to have originated from. E-mail address may not be too long.

E-mail Body:

This text will be sent in the e-mail to the consignee. This text can include information about the individual order.

The following Information from the order header can be placed in the email:

Description	Body Text Code
Order Number	%ORDER%
Reference Number	%REFERENCE%
Purchase Order	%PO%
Bill of Lading	%BOL%
Ship To Name	%SHIPTONAME%
Ship to Address Line 1	%SHIPTOADDR1%
Ship to Address Line 2	%SHIPTOADDR2%
City	%SHIPTOCITY%
State	%SHIPTOSTATE%
Postal Code	%SHIPTOPOSTALCODE%
Carrier	%CARRIER%
Delivery Service	%DELIVERYSERVICE%
Date Shipped	%DATESHIPPED%
Product Number	%PRONUMBER%
Load Pro Number	%LOADPRONUMBER%
Load Trailer	%LOADTRAILER%
Load Seal	%LOADSEAL%
Load Bill of Lading	%LOADBOL%
Pass-Thru Char 01 thru 20	%HDPASSTHRUCHAR01%, Etc.
Pass-Thru Number 01 thru 10	%HDPASSTHRUNUM01%, Etc.
Pass-Thru Date 01 thru 04	%HDPASSTHRUDATE01%, Etc.
Pass-Thru Dollar 01 thru 02	%HDPASSTHRUDOLL01%. Etc.

This information must be formatted with a % at the beginning and end.

Example Body Text:

Thank-you for your order!

DATE: %DATESHIPPED%

ORDER: %ORDER%

CARRIER: %CARRIER%

SHIPPED TO:

%SHIPTONAME%


%SHIPTOADDR1%

%SHIPTOCITY%, %SHIPTOSTATE% %SHIPTOPOSTALCODE%

After the body of the email, a heading labeled “Detail” will list each item for the order and the quantity shipped.

In the case of small package orders, following the detail, there will be a heading reading “Tracking Number(s)”. Following this heading will be a list of tracking numbers that shipped on the order. Each tracking number will be on a line by itself.

The email will be sent once the load has been closed. To resend the email, click



on the Load screen.

Example Order and Email:

Order 370215-1 for Customer INA

Order Info	Shipping	Summary	Comments	Ship To	Addl. Info	Transportation	Ship Dates	History	Billing
Order ID: 370215	Ship ID: 1	Type: 0	Customer ID: INA	Cust PO: PO887766	Reference: 987432				
To Facility:	Appointment Date/Time:	RMA:	Bill of Lading:						
Status: Shipped	Status by: ANN	Status Update: 10/1/2013 02:03 PM	Priority: Normal	Shipper: <input type="checkbox"/> One-Time					
Load: 201629	Stop: 1	Shipment: 1	Load Status: Shipped	Load Appointment Date/Time:					
						<input type="checkbox"/> Has Consumables			
Wave: 213155									
<input type="button" value="Print Receiver"/> <input type="button" value="Reprint PO Confirmation"/> <input type="button" value="Print Order Check"/> <input type="button" value="Items..."/> <input type="button" value="Cancel"/> <input type="button" value="Print Pack List"/> <input type="button" value="Duplicate Order"/> <input type="button" value="Print COA"/> <input type="button" value="View Attachment Tab"/> <input type="button" value="View Plates"/> <input type="button" value="Create Overs"/>									
Legend: Hazardous Over Short Cancelled									
Grid Actions									
Drag a column header here to group by that column									
Item	Lot Number	Order Qty.	UOM	Rcvd Qty.	Ship Qty.	Entered UOM	Entered Qty	Ordered Item	Status
► APPLE		5	Case		5	Case	5	APPLE	Active
BREAD		25	Each		25	Each	25	BREAD	Active
CAKE	766766	0	Case		Case		10	CAKE	Active
PEPPER		5	Case		5	Case	5	PEPPER	Active
PRUNE		0	Case		Pallet		1	PRUNE	Active
TAFFY		10	Case		10	Case	10	TAFFY	Active
6		45		0	45				
< >									
LINUX2TEST Facility ZET (Last Update by ANN at 10/1/2013 02:03 PM)									

Subject: Order Ship Confirmation (Order #370215-1)

Thank-you for your order!

DATE: 01-OCT-13


ORDER: 370215-1

CARRIER: CONWAY FREIGHT

SHIPPED TO:
San Diego
1750 CAMINO DEL RIO NORTH
SAN DIEGO, CA 92108

Order Detail			
Item	Description	Qty	UOM
APPLE	Apple	5	CS
BREAD	BREAD	25	EA
PEPPER	PEPPER	5	CS
TAFFY	taffy	10	CS

Customer Email on Shipment Close



This function sends emails to Customers when an outbound load is closed. Configurable options allow email to be adapted for the recipient. This configuration uses the Oracle emailing functionality used elsewhere in Synapse.

The Email Body will accept the following wildcards:

Body Text Code	Description
%CARRIER%	Carrier code from the load closed
%CARRIERNAME%	Full name of carrier from load
%TRAILER%	Trailer number for load closed
%LOADBOL%	BOL number
%SEAL%	Seal from load
%PRO%	Pro from load
%CLOSEDDATE%	Date load was closed in mm/dd/yyyy format
%CLOSEDTIME%	Time load was closed in 24hr:mm format.
%REFERENCE%	Reference from order(s) associated with load. Returns comma separated list if there are multiples.
%PO%	PO from order(s) associated with load.

Notes:

- When these options are configured for a carrier, an email will be sent to the email address or addresses (comma separated lists will be supported in the To Address) specified when a load of the appropriate type is closed.
- The list of wildcards for this function is less comprehensive than for other emails so note the list above.

Allow Direct Release of Orders

This option enables Direct Release. The Direct Release function commits and releases an order directly to released status, bypassing the normal wave planning and wave release functions

Allow Manual Selection of Picks

This option enables Manual Selection. Manual Selection (allocation) allows you to select specific product in either full or partial license plate quantities in order to fulfill an order without using any allocation rules. Direct Release of Orders is required when Manual Selection is used.

Restrict to Partial Pick Types

If this box is checked the Genpicks processor only generates partial picks even if the pick is for the full plate. This is used by some retail accounts that have some special confirmation procedures.

Grouping Procedures for Wave Planning

The option selected here allows the tagging of orders into a group in order to simplify wave planning. This works in conjunction with the Default Value, ORDER_GROUPING_PROC_PREFIX.

Customer Weight Limits

These settings are intended to allow weight limit warnings by customer. If an order/load exceeds the set limit, a warning will be displayed. You can override the warning and proceed with processing.

Warn on Overweight Orders

Check this box to generate a warning if an order exceeds the Order Weight Limit.

Order Weight Limit:

Enter a weight limit. If an order weight exceeds the limit you enter, a warning message displays.

Warn on Overweight Loads

Check this box to generate a warning if a load exceeds the Load Weight Limit.

Load Weight Limit

Enter a weight limit. If a load weight exceeds the limit you enter, a warning message displays.

Freight Billing Control

These fields are informational only and can be used to link to a customer's Freight Billing System.

Freight Billing Interface

If checked, the other fields can be updated.


Order Header Field that controls Freight Billing Interface

Value that controls Freight Billing Interface

Customer/Facility Email Addresses

This feature allows the entry of multiple email addresses based on facility.

Customer/Shipping/Options-5



Paper based Sortation of Batch Picks

This option is designed to allow a simple, paper-based process for performing sort picks following batch picking.

Allow Paper-Based Sortation

Checking this box enables this option for the customer.

Report

This field defines the report that is generated for this option. This report must have two parameters; Order ID and Ship ID.

Preliminary Pack List Options

When the Preliminary Pack List report is configured for a customer, it will print upon wave release for any orders for that customer. At wave release, you will be presented with a Print dialogue window so that you can select a printer to send the report to. The report will print to the default printer shown in the Printer field on the bottom of the Options-5 screen. If more than one order is on the wave, all pack lists will print to the same printer.

Ship-From Address

These settings are not required. They are flags to trigger the report functionality. Select the address that you want to print on the preliminary pack list.

Preliminary Pack list Format:

This field identifies the report file path.

Option1, Option 2, Option 3

These are generic fields and can be renamed in the Customer Dictionary. These fields will be informational only and can be used by the report.


Printer

This field identifies the default printer for the pack list report.

Ignore Small Package Weight

If this option is selected, the weight captured by MultiShip processing and interfaced back to Synapse will not update the shipping plates.

Customer/Shipping/Instructions




This screen is used to enter free-form text outbound shipping instructions to display on the RF terminal during the shipping process. These instructions can be specific to a consignee.

If “Automatically display instructions when handling” is checked, the RF operator will have the instructions automatically displayed. If the box isn’t checked, an “*” will be displayed and the RF operator can view the instructions by using a function key.

In most installations, the RF display screen is limited to a width of approximately 20 characters. The following rules apply for display of the free-form text area entered via the CRT on the RF displays:


1. A word (contiguous sequence of non-blank characters) will not be split across multiple lines unless the word is longer than the width of the screen.
2. All blanks at the beginning of a line (i.e. left edge of the screen) are removed.
3. All non-printable characters (e.g. carriage return, tab) are replaced by a single blank.
4. Any contiguous sequence of blanks is replaced by a single blank.

Customer/Shipping/BOL Comments



This screen is used to define free-form text outbound instructions to be printed on the Bill of Lading (BOL) during the shipping process. These instructions can be specific to a consignee.

Customer/Shipping/Pack List



Settings Tab

Use this screen to configure a pack list by carrier/delivery service code. This is useful if the customer requires different wording or formatting for individual carriers and services such as next day delivery.

To determine whether or not a pack list is to be printed for a specific order:

1. SYNAPSE first looks at this screen for a match on customer, carrier, and delivery service.
2. If found, the Generate Pack List Y/N and Generate Master Pack List Y/N indicators are examined to see if a pack list should be printed. If the Server radio button is selected, Yes is implied. (Server is used for the VICS BOL server processing used by a limited number of Synapse installations.)
3. If not found, the system then looks for a match based on customer/carrier (and a blank delivery service code).
4. Again, if found, the Generate Pack List Y/N indicator (or master) is examined to determine if a pack list is to be printed.
5. If not found, the system then looks at the pack list indicator (or master) on the Customer/Shipping/Options-3 tab to determine whether or not the pack list should be printed.

Carrier

A carrier entry is required.

Delivery Service

Delivery Service codes are often set up for small package carriers that offer multiple levels of service such as overnight shipping, 2-day air, etc. The Delivery Service field is optional. If the delivery service is left blank, the pack list configuration for the customer/carrier will default.

Pack List Report Format

This defines the directory path and name for the Crystal Report form for the pack list. If left blank, it will use the pack list default for the carrier.

To determine which pack list report format should be used:

1. SYNAPSE follows the search path identified above, and uses the first non-blank format value found in the search path.
2. If after completing the search, no pack list format has been found, the system will then obtain the format value from the System Defaults "PACKLISTREPORT" entry.

Generate After Audit

If this option is chosen, the RF operator doing an RF Shipping Audit (Option 49) can print a packing list report for the carton just audited.


Master Pack List Report Format

This defines the directory path and name for the Crystal Report form for the master pack list. If left blank, it will use the pack list default for the carrier.

To determine which pack list report format should be used:

1. SYNAPSE follows the search path identified above, and uses the first non-blank format value found in the search path.
2. If after completing the search, no pack list format has been found, the system will then obtain the format value from the System Defaults "MASTERPACKLISTREPORT" entry.

By Field Tab



This option allows you to bypass the consignee-based packing list process and base the packing slip format on values identified in the order header. Normally these values will be in a HeaderPassThru field. For example, if Field 1 (a passthru field) on the order header is Target and Field 2 (a passthru field) is 900082, then the packing list prints using the Packing List Format specified.

Orderhdr Field 1:/Orderhdr Field 2:

These values identify the Order Header fields used for matching.

Field 1 Value:/Field 2 Value:

These values identify the values to be matched.

Packing List Format

This defines the directory path and name for the Crystal Report form for the pack list that will be generated.

Customer/Shipping/Audit Locations

The screenshot shows the 'Audit Locations' tab selected in the top navigation bar. The facility dropdown is set to 'ZET' and the audit location is 'AUDIT01'. A message at the bottom indicates 'LINUX2TEST Facility ZET (Last Update by ANN at 10/28/2013 11:06:36 AM)'.

Facility	Audit Location	Last User	Last Update
ZET	AUDIT01	ANN	10/28/2013 11:16:29 AM

Facility

The staging locations are defined by facility. The CRT user must be in the facility to add this information. Only one location per customer per facility is allowed.

Audit Location

This field defines the STAGING location for shipping LP's that failed the shipping audit process. The RF operator will not be able to audit a LP for a customer, if this location is not defined.

Customer/Shipping/Carriers

The screenshot shows the 'Carriers' tab selected in the top navigation bar. The ship type dropdown is set to 'T', from weight is '15001', to weight is '42500', carrier is 'KNIG', delivery service is 'Truckload', and assigned ship type is also 'Truckload'. A message at the bottom indicates 'LINUX2TEST Facility ZET (Last Update by ANN at 10/28/2013 11:06:36 AM)'.

Ship Type	From Weight	To Weight	Carrier	Delivery Service	Begin Zip	End Zip	Assigned Ship Type	Last User	Last Update
T	15001	42500	KNIG				Truckload	ANN	10/28/2013 11:31:03 A
L	100	15000	ABF					ANN	10/28/2013 11:30:15 A

The Carriers tab allows you to set up preferred carriers for a customer based on Ship Type, Weight, Delivery Service, and Zip Code.

Ship Type

Enter the Ship Type for the preferred carrier.

From Weight/To Weight

This value is entered in pounds. From Weight must be less than or equal to To Weight. Weight ranges cannot overlap.

Beg Zip/End Zip

This value is a 5 digit Zip code. From Zip must be less than or equal to To Zip. Zip code ranges cannot overlap.

Carrier

A valid carrier from the carrier table must be selected.

Delivery Service

Enter the delivery service for the carrier, if applicable.

Assigned Ship Type

Enter the assigned ship type, if applicable.


Preferred Carrier Processing

If the carrier is not defined on an order and a preferred carrier exists, the preferred carrier is added to the order with no warning message.

1. This can be the case in EDI orders. The carrier is still a required field on all manually entered orders.
2. The system will first see if there is a match for the consignee-defined preferred carrier. If that match does not exist, the system looks at the carriers defined at the customer level.
3. If the carrier is defined on the outbound order, but the weight or consignee zip is within the range for the preferred carrier (if one exists), a warning is added to the applications messages log. The warning gives the preferred carrier ID. Changes to the carrier field on the order must be made manually.

Customer/Shipping/Notification

This configuration provides the ability to associate Shipping Notification exports with a customer's Ship-To consignees.



Ship To:

- Enter “1TIME” to indicate the export is associated with One-Time Ship-To's or
- Enter a specific Ship-To consignee (double-click to perform a consignee lookup).

Order Type

Indicate if the export applies to:

- Outbound
- Return-To-Vendor
- Transfer Orders
- All

Export Mapping Format

Choose the export format from the drop-down list.


Each time an order is shipped, the system will check these entries to determine if an export request needs to be generated.

Customer/Shipping/SIP Settings and Consignee


These tabs support a customer-specific interface to a SPS Commerce Product. This interface does not affect any current EDI processing. Please contact the TSD at Zethcon for specific information.



You can define the EDI transactions by consignee on the Consignee tab:



Customer/Shipping/TMS




Import Formats/Export Formats

This tab supports a customer-specific interface to the Transynd Transportation Management System product. This interface does not affect any current EDI processing. Please contact the TSD at Zethcon for specific information.

Bed Bath & Beyond Routing Setup

This tab supports a customer-specific interface to the routing guide for Bed, Bath & Beyond. This interface does not affect any current EDI processing. Please contact the TSD at Zethcon for specific information.

Customer/Shipping/Custom BOL



Custom BOL # Definition

This screen allows the creation of a custom BOL number for an order. It can use any fields from the order header, customer and/or loads tables. It also can use any custom selectable functions that return a varchar2 type value.

The definition can be any valid SQL select statement. There are three tables that can be referenced in the definition specified by a shortcut:

- O - Orderhdr
- C - Customer
- L - Loadno

Any column in these three tables can be used in the definition.

Testing

You can test the definition on the screen. Enter an orderid-shipid in the ‘Test Orderid-Shipid’ field and click the Test Custom BOL # button . This will first test the syntax of the definition, and show any errors. If the syntax of the definition is valid the resulting custom BOL will appear.

Using the Custom BOL


The function defined for retrieving the custom BOL for an order is zedi.get_custom_bol(orderid, shipid). It is a selectable function that returns a varchar2 value.

If the custom BOL is not defined, it returns the first defined of the following:

1. loads.billoflading
2. orderhdr.billoflading

3. orderid-shipid

Customer/Shipping/Carrier Note



This screen allows Export Ship Notifications to be specific by carrier.

Carrier

Enter the carrier. You can double click to select one from a list.

Order Type

Indicate if the export applies to:

- Outbound
- Return-To-Vendor
- Transfer Orders
- All


Export Mapping Format

Choose the export format from the drop-down list.

Customer/Billing

See the **SYNAPSE Billing Concepts Manual** for Options, Address, Rate Summary Instructions, Approval Limits, and Invoicing.

Customer/Dictionary



This screen allows for the substitution of specific customer jargon or terminology for selected system field names used for CRT screens in SYNAPSE. A typical example would be the replacement of "ITEM" by "SKU" or renaming one of the useritem fields. This dictionary does not affect report headings in Crystal Reports.

Note: See the Setup/Customer/Receiving/Options Tab for information on customizing RF labels.

System Field Name

Select the value for customization from the drop down list including:

- Item
- LotNumber
- PO
- Serial Number
- UserItem 1, 2, 3
- UserAmt 1, 2
- Dtl and Hdr "PassThru" Values – These are used in EDI processing where values are imported for order header and order detail processing. Setting Window Label Values here will make the order information more meaningful.
- Item Pass Thru - Char and Num – These values are on the Item Maintenance/Item Specs/Specs tab. Setting Window Label Values here will make the item setup information more meaningful.


- Preliminary Packlist Options 1, 2, 3 – These values are used in the preliminary pack list processing on the Shipping Options-5 tab.

Window Label Value

This is the value that will appear on the CRT screen in place of the System Field Name.

Customer/Labeling

Customer/Labeling/General



Entries on this screen associate a customer or customer/consignee combination with a specific label profile for the printing of output labels.


Consignee

The consignee information must first be entered on the Setup/Consignee Maintenance screen and then be associated with this customer on the Setup/Customer/Shipping/Options –1 tab. This field is optional.

Label Profile

Choose this value from the label profiles defined on the Setup/Label Profile screen.

Customer Labeling/Labeling Options



LP Labeling

This screen is used as part of the optional automatic lip label generation in the Transloading process. It provides functionality to produce a label upon the arrival of an Inbound Customer load. The label is created in labeling software (Nicelabel). The label produced is essentially a license plate containing a significant amount of human readable and bar coded information, such as PO, item number, etc. This is also referred to as Front End Labeling (FEL).

Print Plates on Load Arrival

Checking this box will trigger the label creation at the beginning of 1-Step Receiving.

System Generated Plates

Checking this box will trigger the label creation after the item is received in 1-Step Receiving. Generating the labels after receipt has the potential to add more specific information on the label.

Label Profile for Plate Printing:

Select the appropriate Label Profile. These are defined on the Setup/Label Profile/Label Profile Maintenance Screen.

Default Handling Type:

Select the Default Handling Type for the receipt. These values are set up using the Setup/Handling Type/Receipt Handling Types Definition screen.

SSCC Options

Order Header Field that contains Manufacturer UCC Code

This is used by specific labeling procedures to identify the Manufacturer UCC code from an order header field and not from the code identified on the Customer/Name tab.


Casepack From Uom/Casepack To Uom

These fields are used to determine how to obtain the casepack quantity when producing SSCC labels. If item values exist, they will override these customer-level values. If no values are present, the defaults are PCS and CTN.

Multi UOM Labels

This option allows you to set up a hierarchy for printing labels if you have multiple units of measure.

Customer/Facility Settings



This configuration is used to support customer processing in multiple facilities within the same installation of SYNAPSE. The values for customer defaults are set here by facility.

Note: The CRT operator must be in the corresponding facility to make changes. Use the right click Change Facility option. To add an entry, use the Plus/Add symbol on the lower tool bar.

Facility

This is the specific facility for the settings.

Allocation Rule

The customer-default allocation rule is set here. This is selected from the facility list entered using the Setup/Facility/Allocation Rules Screen.

Replenishment Allocation Rule

The customer-default replenishment allocation rule is set here. This is selected from the facility list entered using the Setup/Facility/Allocation Rules Screen.

Putaway Profile

The customer-default putaway profile rule is set here. This is selected from the facility list entered using the Setup/Facility/Putaway Profiles Screen.

Returns Location

This field defines the customer-default staging location for returns processing for the selected facility. Staging locations must be defined for the facility using the Setup/Facility/Location/Location Maintenance screen.

Wave Profile

Wave Profiles are set up on the Setup/Facility/Wave Profile Screen. The profile allows multiple wave templates to be specified for automatic planning of imported orders. Wave Profiles can be defined for a facility, specifying a prioritized list of wave templates. The wave profiles are associated with a customer and facility level using this field.


Packlist Printer

This is the default pack list printer for non-MultiShip pack list printing.

Freight Billing

These fields are used as part of the Freight Billing Module. ?????

Customer/Handling



This configuration is designed to allow inventory to automatically change inventory status when inventory is moved into and removed from certain location types.

Once all necessary settings are made to enable the functionality, product moved into a location with the specified location type will be automatically adjusted to the inventory status configured as the Entering status. Later, when the product is moved out of the location, it will be automatically adjusted again, this time to the Exiting inventory status.

1. These adjustments will normally occur via RF moves or inventory moves performed through the Aggregate Inventory Re-warehousing screen.
2. Inventory adjustments for a location will trigger the functionality but can be avoided by adding “IA” as an excluded task.
3. Should a mixed pallet containing both product configured and product not configured for the functionality be moved into a location of the defined type for the configured item, only the configured item will be adjusted. When the adjustment is made, the Adjustment Reason will be recorded per the setup of the Reason mentioned above.
4. Each of these movements will be associated with a corresponding Business Event. “ENTR” for the Entering Auto Adjust and “EXIT” for the Exiting Auto Adjust.
5. When triggered, the adjustment occurs and if an event is configured, it will create a Misc. Order associated with the charge. As long as that Misc. Order is not processed, additional charges will accumulate against the same Misc. Order.

Location Type:

Use the drop down box to select a location type. This is the type of location that will be used to trigger the status change.

Exclude Task Types


This field allows for a comma-delimited list of task types that should **not** generate an adjustment or event.

Inventory Status - Upon Entry/Upon Exit

Enter the Inventory Status to update the entering/exiting inventory.

Adjustment Reason - Upon Entry/Upon Exit

Enter the Adjustment Reason code for the Entry/Exit inventory adjustment transaction.

Customer/Trading Partners

The grid on this tab is used to maintain a list of trading partners (other valid Synapse customers) associated with a customer. The table is used for export reporting and order inventory data for both the trading partner customer(s) and the associated “master” customer. The same trading partner can’t exist for multiple customers.

If a customer is selected as a trading partner, this information will be displayed at the top of the Setup/Customer screen as shown below.

Customer 2500-Warehouse 2500 (Trading Partner of INA)

Name	Receiving	Shipping	Billing	Dictionary	Labeling	Facility Settings	Handling	Trading Partners		
Customer ID: 2500	Status: Active	Clone	Rates	Groups	Items	[Navigation Buttons]				
Name: Warehouse 2500	Phone: 630-748-3100	Consumables Owner:								
Lookup: 2500	FAX: 847-318-0807	<input type="checkbox"/> Use Expanded WebSynapse fields <input type="checkbox"/> Suppress Anniversary Date <input type="checkbox"/> Aggregate Inventory <input checked="" type="checkbox"/> Require Cycle Count Item <input checked="" type="checkbox"/> Require Cycle Count Lot <input type="checkbox"/> Require Physical Inventory Item <input checked="" type="checkbox"/> Require Physical Inventory Location <input type="checkbox"/> Allow Extra Picking <input type="checkbox"/> Allow Load Assignment								
Contact: Joe Smith	E-Mail:									
Address: 1234 Main Street	Primary CSR:									
City: Lombard	State/Province: IL	<input type="checkbox"/> Track Pallets	<input type="checkbox"/> Bill For Pallets	<input type="checkbox"/> Collect Pro Numbers <input type="checkbox"/> Allow Pick Passing						
Postal Code: 60148	Country: USA	<input type="radio"/> Yes <input type="radio"/> No <input checked="" type="radio"/> Warn <input type="radio"/> Hold								
Master Account:	Manufacturer UCC Code:	Recent Order Days:	Min 0-Qty Weight:	Duplicate Order Reference Allowed: <input type="radio"/> Yes <input type="radio"/> No <input checked="" type="radio"/> Warn <input type="radio"/> Hold						
Unique Order Identifier: <input checked="" type="radio"/> Reference <input type="radio"/> Reference and PO										
Reduce Order Qty By Cancel Amount: <input type="radio"/> Yes <input type="radio"/> No <input type="radio"/> Default										

LINUX2TEST Facility ZET (Last Update by SWINCELL at 10/21/2011 5:03:52 PM)

Item setup

Note: Many of the values set up on Item Setup screens override the customer default and product group default values entered on the Product Group and Customer screens.

Item Specs/Name

Item	Description	Abbreviation	Status	Rate Group	Hazardous?	Product Group
APPLE	Apple	APPLE	Active	ITEM	N	
BEER	BEER	BEER	Active	ITEM	N	LIQ
BERRIES	Mixed Berries	Berries	Active	ITEM	N	
BOXES	BOXES	BOXES	Active	ITEM	N	
BREAD	BREAD	BREAD	Active	ITEM	N	
BUTTER	BUTTER	BUTTER	Active	ITEM	N	
CAKE	Cake	CAKE	Active	ITEM	N	
CHEESE	Cheese	CHEESE	Active	ITEM	N	
CHEESE KIT	Cheese Kit	Cheese Kit	Active	ITEM	N	
CUPS	MULTTRANOL 3900	PARTIAL	1002957	Inactive	ITEM	N
GRAPES	grapes	GRAPES	Active	ITEM	N	
LBS-FLOUR	Flour by the pound	LBS-FLOUR	Active	ITEM	N	

LINUX2TEST Facility ZET (Last Update by ANN at 10/21/2013 9:51:25 AM)

Customer ID

This is the customer ID for this item. The customer must be entered into SYNAPSE prior to adding items.

Item

This needs to be a unique item ID within this customer.

Although the CRT application supports a length of 20 characters for the item, the RF application only allows the entry of 16 characters for an item due to the size constraints of the RF screen. The Item Alias processing needs to be used for the RF entry for item ID's greater than 16 and less than 21 characters.

WARNING: The use of a single quote or double quote (' or "), "&" or "%" in the item id will cause processing issues.

Note: This may not be a complete list of all special characters that may cause issues, but these special characters cause known issues. Item IDs that start with a leading period (.123AXX) may need a special update.

An item can only be deleted using a purge process.

Needs Review

Check this box to indicate that the item data is incomplete or requires manual review. A display of items requiring review can be requested when doing an item lookup.

This designation is informational and does not affect processing for the item. This designation is useful for customers that provide item setup information via EDI.

Description

This is a free form description of the item.

Abbreviation

This is an abbreviated description of the item.

Status

The Status values are maintained in the ItemStatus validation table.

- Active
- Inactive
 - 1. The stock status export reports both active and inactive items and any inactive items that remain in inventory.
 - 2. The inactive status allows an item to be inactivated so that no future receiving can occur, but any items remaining in stock can still be shipped.
 - 3. An inactive item cannot be purged until history data referring to that item has been purged. That is, all license plates, shipping plates, order items, etc. in the entire database must be purged before the item is eligible to be purged from the system.
- Pend - Pending Review. The item is considered Inactive. This status is used when item definition information is imported via EDI and is used in conjunction with the “Needs Review” check box. It allows the CSR’s to identify the pending items for review.

Product Group

Product Group is a layer of data between Customer and Item. Each product group is unique to a customer. Product groups support items with similar characteristics. For example, for an electronics customer, three product groups might be defined: one for high-end electronic equipment that typically require serial number tracking, another for children’s electronic toys

that may need value added services, and a third for technical manuals that may become parts of kits.

If applicable, select the product group for this item. If a product group is chosen, the product group values will become the default values for the item.

Product groups are defined on the Customer/Product Group screens.

Rate Group

Items are normally assigned to a customer-level defined rate group for billing purposes. Rate Groups are defined on the Customer/Rate Group screen. See the Synapse Billing Concept Manual documentation for information on rate group selection.

If no value is selected or the “Use Default” option is selected, SYNAPSE will default to the value displayed in the Default field. A Default Rate group for the customer needs to be configured for an item to be set up.

Kit Type

A kit is an item that is created by combining or modifying other items.

- If an item is a “kitted item”, the “Kit by Item”, “Kit by Class”, “Component Template” or “Simplified Kit” radio button is indicated on this screen. Specific Kitting item set up information is included in the User Manual documentation on Kitting. If an item is marked other than None, then the Kit Setup must be in place prior to outbound order processing.
- If an item is a component of a kitted item or not used in kitting, the “none” radio button should be selected.

Require Cycle Count Item

If the "Require Cycle Count Item" is set, when you cycle count LPs if you do not enter an item (and customer) and on the LP, you will get an error message. If the flag is not set, then the customer, item, description and lot are displayed and you can either just press enter or override any of the fields (except for description).

Require Cycle Count Lot

When this option is checked, the count tasks will follow the normal cycle count requirements for lot. When the option is unchecked, the lot number will appear on the screen during a cycle count and you won't have to enter it.

Require Physical Inventory Item

When this check box is selected, the RF operator will be required to enter all the data elements for the LP being counted, such as Customer, Item and Lot. This is the default functionality for Physical Inventory processing. When the check box is NOT selected, the data will be auto populated when the LP is scanned. This feature works similar to the Require Cycle Count Item option.

Require Physical Inventory Lot

When this option is checked, the Physical (PI) tasks will follow the normal PI requirements for lot. When the option is unchecked, the lot number will appear on the screen during a cycle count and you won't have to enter it.

Display Active Only

When this box is checked, only items with a status of Active appear in the grid at the bottom of the screen.

Additional Information

Hazardous Symbol




This symbol will appear for items set as Hazardous. The hazardous items are color-coded in the grid at the bottom of the screen.

Clone

This function allows you to clone a customer item to create a new item for the same customer or a different customer. This is useful in item setup, when a customer introduces a new or replacement item that has similar characteristics to an existing item, when an existing item shifts to a new customer and for testing.




- Click the Clone button . The following screen appears:



- Enter the data base that you are copying the item to. Use the drop down to select one from a list.
- Enter a customer ID.
- Enter an item ID.

Note: A new item ID must be entered. If the customer ID is changed, a new item ID can be entered or the same item ID can be entered.

- Select the Clone Item Alias and/or the Clone Item PickFront check boxes.
- Click OK. A confirmation window appears.




- Click Yes to continue.
- If necessary, update the cloned item information (i.e., description, abbreviation, rate group, etc.).

The following information may not be cloned to the new item and the information must be entered manually after the cloned item is created:

1. Substitutes Tab – not cloned
2. Kitting Setup information if the Customer ID is new, since this is based on item information for the current customer.
3. Rate Group and Product Group - before cloning for a new Customer ID, the procedure verifies the existence of a similarly named Rate or Product Group for the new customer. If it exists for the new Customer ID, the field is left with the group ID, otherwise it is set to null.

Item Specs/UOM



Important Warning Messages

Inventory Exists. (UOM changes not recommended) and Inventory Exists. No UOM changes allowed.

One of the above warning messages will appear if there is existing inventory in the facility.

Generally the existing inventory needs to be adjusted off in the original unit of measure (UOM) and then added back to the system with the correct UOM.

Although the system will allow changes to the UOM if the “Allow UOM Changes (Supervisors Only)” box is checked on the Item Specs tab, the existing inventory (license plates) will not be updated.

The as of inventory tables that are used for Renewal Storage Billing and Item Activity reports will not be updated and may cause reporting and billing issues.

Base UOM

This defines the unit of measure and the related item characteristics for the smallest unit of measure that is processed in the system. UOM values are defined in the “UnitsOfMeasure” validation table.

Cubic Inches

This is the cube of the base UOM in inches. This fills in automatically when you enter the Dimension in Inches fields.

User Amount 1, User Amount 2

User Amount 1 and 2 are item specific dollar values that additionally define the item. The labels for these fields can be overridden at the customer level using the Dictionary tab. Note: These fields can be used to set receipt overage limits for receipt and return orders on the Customer/Receipt/Overage tab.

Velocity

- A – This velocity is used for the fastest moving items.
- B - This velocity is used for the medium moving items.
- C - This velocity is used for the slowest moving items.

Additional Velocity Information:

1. If the “Use Velocity” option on the Putaway Profile is set to “Yes”, the velocity code of the received item is considered in choosing a location for system directed putaway.
2. If the ABC Cycle Count Processing is used, this value may be updated based on the ABC calculations. Refer to the chapter in the SYNPASE User manual for information about the ABC Cycle Count processing for an explanation of the calculations.
3. The values for this field are maintained in the “ItemVelocityCodes” validation table and must be restricted to the values of A, B and C to coordinate with the ABC Cycle Counting processing.

Pick To Type

The following values are in the “PickToTypes” validation table:

- Full - Pick until the container/conveyance is full based on the operator’s assessment. The container type is not considered.
- LBL - Pallet – Separate Label Required
- PACK - Pick and Pack to a carton (the container type defined for this item); the pick task generation logic will take into account the size and weight restrictions of the specific container type selected for this item when creating pick tasks.
- PAL - To Pallet - Pallet as a container is based on the pallet size defined on the Setup/Container Types screen.

- **TOTE** - Pick to Tote – Totes are permanent containers that have LiP identification. A pack step is used to build the final shipping plate.

Container Type

The value should reflect the container to be used for picking, packing and shipping this unit of measure for the item. These values are maintained using the Setup/Container Types screen.

If a container group is chosen, the system will look for the smallest container for the product to fit into.

Additional Information for Pick to Type and Container Type

Synapse can assist in maximizing carton cube by using:

1. **Pick to Pack Logic.** When utilizing this feature, the system is configured so that each item is associated with a carton or carton group into which it is to be packed. Then, when you pick the items, the system suggests cartons from the item configuration that maximize carton cube and weight capacities for the items. The result is a direction to use certain cartons, for example, 1 Small and 2 Mediums.
2. **A Packing Station.** If the operation prefers a packing station, Synapse supports picking to reusable totes and CRT directed packing, including instructions. For every package that is produced, Synapse can always report the cube of the contents of that package and the weight, including tare where configured.

Dimension in Inches

These values can be used for interfaces to manifesting software to determine if an item qualifies for oversize package rates. There is no validation that the dimension fields calculate to an entered cube value for the item, but the values entered here will be used to calculate the Cubic Inches field. These fields are optional.

Weight

Lbs.:

This is the weight of the base UOM in pounds.

Kgs.:

This is the weight of the base UOM in kilograms. This is automatically calculated from the Lbs. field entry.

Tare Weight

The tare weight for the empty container and/or packing materials without the weight of the inventory it contains. This field is optional and for reporting purposes only.

Lbs.:

This is the tare weight of the base UOM in pounds.

Kgs:

This is the tare weight of the base UOM in kilograms. This is automatically calculated from the Lbs. field entry.

Pallet Definition**Limit Pallet to Quantity**

If this check box is selected, the system will not allow you to build a pallet, using the RF Option 13 - Build Pallet, with a quantity greater than that specified in the Quantity and UOM fields. If this box is not selected, the information in the Quantity and UOM fields will not affect processing, but can be used for reporting and labeling purposes.

Quantity:

The Quantity of the UOM per pallet. See above.

UOM:

The unit of measure for the quantity on the pallet. See above.

Pallet Name:

This field is used for the name or size of the pallet. The length is 20 characters. This is informational only and can be used for reporting and labeling purposes.

Additional UOM's other than the Base UOM

All units of measure that will be processed for this item must be defined here. If there is a single UOM for an item, no information is entered here.

Sequence

Each sequence defines the order for the relationships. The sequence should go from the smallest to the largest UOM. It is normally best to start with sequence number 10 and increment by 10 to leave room for changes in the future. This field is required.

There are/of these/in a

Defines the quantity ("there are" column) of the lower UOM (defined in the "of these" column) in the higher UOM (defined in the "in a" column). For example, *there are 25 of these cs in a plt*. These fields are required.

Pick To

This is the pick to type (see above) for the item. This field is required.

Velocity

This is the item velocity (see above). This field is required.

Note: All of the other fields for the additional UOM's are optional.

Item Specs/Specs

The screenshot shows the 'Customer INA - Item Maintenance for PEANUT TAFFY' application. The 'Specs' tab is active. Key visible fields include:

- Shelf Life:** Min Sale Life: 30 Days
- UOM:** Box
- Label Qty for Label UOM:** 1
- NMFC:** 39960-02
- LTLFC:** 2D
- Units of Storage:** 2D
- Reorder Point:** 0
- NMFC Article:** 0
- TMS Commodity:** 0
- Min 0-Qty Weight:** 0.5
- Default:** 0
- Stack Height:** 3 Pallets
- Stacking Factor:** 1
- Expiration Action:** Contact Cust
- Summarize Lots:**
 - Receipt Invoice
 - Renewal Invoice
 - Bill of Lading
 - Accessorial Invoice
- Last Cycle Count:** 0
- Critical Inventory Levels:**

Level 1	Level 2	Level 3
0	0	0
0	0	0
- Additional Item Info:**

Char 01:	Char 06:	Number 01:	Number 06:
01	06	1	6
02	07	2	7
03	08	3	8
04	09	4	9
05	10	5	10

LINUX2TEST Facility ZET (Last Update by ANN at 10/29/2013 9:43:15 AM)

Shelf Life

This field defines the shelf life for the item in days. The maximum value is 999. This field is optional.

This field is not used in the actual LP expiration processing but is used in receiving to set an expiration date for a plate.

- If an item is setup to capture expiration dates, the expiration date will be populated on the license plates using the captured date.
- If an item is setup to capture manufacture dates and there is a shelf life configured, the expiration date on the license plates will be populated with the manufacture date plus the shelf life number of days.
- If no date is set for capture but a shelf life is configured, the expiration date is populated by adding the shelf life number of days to the creation date for the license plate.

Min Sale Life

This field is used in conjunction with the Verify Sales Life function. It allows you to automatically place stock on hold upon receipt if it is going to expire within a specified number of days.

For example, if an item you are receiving is going to expire in 5 days you may not want to make it available for shipping. By the time you process it through the warehouse, ship it and the consignee receives it, the product may already have reached its expiration date. If you set the minimum sales life to 10 days, when items that expire in less than 10 days are received, they will automatically be placed in Vendor Compliance (VC) status and won't be available for shipping.

To use this function, the Verify Sale Life check box must be checked on the Customer/Receiving/Options tab, the Min Sale Life Days must be entered and the expiration date must be set to Yes for the item on the Item Specs Receiving Options -1 tab. If you want to use this function for all items for a customer, the expiration date can be set to Yes at the customer level.

Expiration Action

This field defines the expiration action for the item. These values are maintained in the ExpirationAction validation table. This is informational only.

Label UOM/Label Qty for Label UOM

Wave Planning uses these fields to create the column "labeluom" in the subtask table. (Note that labeluom is not visible from the subtask screen but is used in the process.) If Label UOM is not null, the Pick to Type for the item is "LBL" and the location is not a pick front, then this column is used to convert pick UOM and pick quantity to a value, which determines the number of shipping plate IDs the picker must enter. If Label UOM is null, then the base UOM is used in the calculation.

This is important for small package orders where the quantities are ordered in eaches but are picked in cases. If this is not set correctly, the picker will be asked for labels for all the eaches, not each carton. The allocation rule option, Whole Units Only, must be on for this to work properly.

Unit of measure values are defined in the "UnitsOfMeasure" validation table. This field is optional.

See the Synapse User Manual for the effect this value has on the Mass Manifesting Processing.

NMFC

This field defines the National Motor Freight Class Code for the item. These values are defined using the Setup/NMFC Codes/NMFC Code Definition Screen. This field is used in Bill of Lading processing and is optional.

LTLFC

This field defines the LTL Freight Class Code for the item. These values are defined using the "LTLFreightClass" validation table. This field is used in Bill of Lading processing and is optional.

Units of Storage

These values are used in Pick Front Management processing. They define the acceptable sizes (based on defined Units of Storage) for potential pick fronts for an item. Multiple UOS values can be chosen. This field is required if the Pick Front is added or updated without an assigned Pick Front location.

Reorder Point

Used for reporting purposes. This field is informational only and optional.

NMFC Article

This field is used for an interface with the Transynd Transportation Management System.

TMS Commodity

This field is used for an interface with the Transynd Transportation Management System.

Min 0 – Qty Weight

If a plate exists with no quantity and still has an existing weight (i.e., catch weight items), this parameter allows the plate to be automatically deleted if it is below the minimum weight set. The weight is an absolute value and can be set for whole numbers or decimals.

Country of Origin

Country Code values are defined in the “CountryCodes” validation table. This field is informational only and optional.

Summarize Lots

In billing processing, line item charge processing considers each lot number as a line item and applies charges accordingly. This can be turned off at the item level for receipt, renewal and accessorial invoices by checking the Summarize Lots box for the appropriate invoice type(s). This also applies to Bill of Lading processing.

Stack Height

Enter the maximum stack height for a pallet of the item. This field is optional and used to determine the pattern for the 1st Pallet Height (H) putaway method.

Stacking Factor

This field assists in controlling how the system sets location assignments for Flex Pick items. This can be used for grouping the heavier product in the front of the pick line or for getting like pallet pattern items together. There are many other reasons why items may need to be grouped. This field accommodates up to a 4 digit number and will assign items with the lowest factor number first. Items with the same Stacking Factor number will be assigned in item sequence. Items without a Stacking Factor will be assigned after items that have a number assigned.

Treat Label UOM remainders as separate

This option allows you to print labels for less than a full UOM. For example, if the base unit of measure is Each and there are four Eaches to a Case and labels are printed by Case, than an order is for a quantity of 6 Eaches, two labels will print – one for the full case of four and one for the remaining two Eaches.

Allow UOM Changes (Supervisors only)

This must be checked to allow UOM changes for items with existing inventory. Making UOM changes can cause issues with the as-of inventory. The as-of inventory is the basis for activity reporting and some renewal billing methods.

Last Cycle Count

This field displays the date and time the last cycle count was completed. You can double click this field to navigate to the Cycle Count Activity Look-up screen.

Critical Inventory Levels

The Critical Inventory Level area of the screen is used to define the number of days for the Level 1, 2 and 3 fields. If the levels are not specified, they will default to 30, 60, and 90 days respectively. This information is used to process the Critical_Product_Inventory.rpt. Crystal Report.

Additional Item Info

The Additional Item Info fields consist of ten character fields and ten numeric fields. The character fields have a max length of 255. The fields are informational only and are typically used to hold additional description information for the item.

The labels of the pass-thru fields can be changed using the Dictionary tab in Customer Maintenance Setup. Note that they are labeled ITMPASSTHRU1, etc. in the System Field Name for the Dictionary function.

Item Specs/Receiving

Item Specs/Receiving/Options – 1

The screenshot shows the Synapse 2 software interface for Customer INA - Item Maintenance for SOAP. The 'Item Specs' tab is selected. The 'Receiving' tab is active. The 'Required Upon Receipt' section is expanded, displaying the following configuration:

- Lot #:** Use Default (dropdown), Min Seq: [] Max Seq: [] Default: N - Not Required
- Serial Number:** Use Default (dropdown), Min Seq: [] Max Seq: [] Default: N - No
- User-Defined 1:** Use Default (dropdown), Min Seq: [] Max Seq: [] Default: N - No
- User-Defined 2:** Use Default (dropdown), Min Seq: [] Max Seq: [] Default: N - No
- User-Defined 3:** Use Default (dropdown), Min Seq: [] Max Seq: [] Default: N - No
- Manufacturing Date:** Options: Yes, No, Default: N. Bulk Cycle Counting: Required (checkbox checked).
- Expiration Date:** Options: Yes, No, Default: N. Bulk Cycle Counting: Required (checkbox checked).
- Country Of Origin:** Options: Yes, No, Default: N.
- Use Catch Weight:** Options: Yes, No, Default: N. Outbound Catch Weight: N.
- Capture Pick UOM:** Options: Yes, No, Default: N. Inbound Catch Weight: Gross (radio button selected).

Required Upon Receipt

Lot

The following options are available:

- Yes – Lot number must be recorded for inbound inventory.
- AutoSeq – Lot number is automatically assigned to inbound inventory. A minimum and maximum number can be entered.
- Also Outbound – Lot number must be recorded for both inbound and outbound inventory.
- Some Outbound – Lot number may be optionally entered on outbound orders.
- Upon Pick – Lot number must be recorded during picking.
- Not Required – No lot number tracking is performed.

Lot number options and associated processing are described in the table below:

Option	Definition	Lot ID Required for Inbound Order Entry	Lot ID Must be Entered During Receiving	Lot ID Required for Outbound Order Entry	Lot ID Must be Entered During Outbound Shipping
N – Not Required	No lot # tracking is performed	No	No	No	No
O – Also Outbound	Lot # must be recorded for both inbound and outbound orders	Yes	Yes	Yes	No
P – Upon Pick	Lot # must be recorded at pick	No	No	No	Yes
S – Some Outbound	Lot # can be recorded for outbound order	Yes	Yes	Optional	No
Y – Upon Receipt A - AutoSeq	Lot # must be recorded upon receipt	Yes	Yes	No	No

Serial

- Yes – Serial number must be recorded for inbound inventory. If duplicate serial numbers are not allowed, this should be set via a format validation rule.
- No – No serial number tracking is performed.
- Upon Pick – Serial number must be recorded during picking.

User 1, User 2, User 3

User 1, 2 and 3 fields contain information that is based on customer item requirements. For example, if a manufacturer of paint requires the capture of a color code, one of the user-defined fields can be designated for this purpose. RF-screen Display Labels and CRT-screen Labels can be defined to more clearly present the meaning of the user-defined fields.

- Yes – User field value must be recorded for inbound inventory.
- No – No User field value tracking is performed.

- Upon Pick – User field value must be recorded during picking.

Note: There is an RF limit of 14 characters for User 1 and User 2. The RF limit for User 3 is 19 characters.

Special Processing for User 2

Location Load (option 91) and Plate Inquiry (option 92) do not process User 2 values.

Special Processing for User 3

The following functions display only the first character of the RF tag (regardless of what was entered in the CRT) and allow for a 19-character entry or display with no space after the prompt:

- 1-Step Receipt - option 11
- Detail Return - option 18
- Inv Adjustment - option 81
- Location Load - option 91
- All types of "Picking"
- Can't Pick
- Shipping Audit - option 49
- Plate Inquiry - option 92
- Kitting – option 61
- Dekitting – option 64

User 3 can also be used as a free form text field to record temperatures or other miscellaneous data for individual lips. This option is only available when the No option is set for User 3 and is used by limited installations.

Manufacturing Date

- Yes – Manufacturing date must be recorded for inbound inventory.
- No – Manufacturing date is not required for inbound inventory.

Manufacturing Date Bulk Cycle Counting

If checked, this will propagate the manufacturing date on the RF Cycle count screen for bulk cycle counting so you have to confirm that it is correct. This date will be required in the Cycle Count.

Expiration Date

- Yes – Expiration date must be recorded for inbound inventory.
- No – Expiration date is not required for inbound inventory.

Expiration Date Bulk Cycle Counting

If checked, this will propagate the expiration date on the RF Cycle count screen for bulk cycle counting so the user has to confirm that it is correct. This date will be required in the Cycle Count.

Country of Origin

- Yes – Country of Origin must be recorded for inbound inventory.
- No – Country of Origin is not required for inbound inventory.

Note: In order to accommodate a 19-character input area for User 3 in Location Load, Country of Origin is not captured.

Auto Sequencing Notes

Auto-sequencing is a feature that allows the assignment of user defined number sequences for Lot Numbers, Serial Numbers and User 1, 2 and 3 in 1-Step Receiving and CRT Receiving (Receive Load). When this is set for a field, license plates created for items will have a value automatically entered into the field.

1. This function is **not** available for Location Load and Location Fill.
2. Multiple Plates received for the same item in the order, should have the same sequence number even if receiving is interrupted and started again later.
3. The sequence numbers can be overridden as part of the receiving process.
4. Format Validation and Parse Rules should not be used in conjunction with this feature.
5. The Manufacture Date, Expiration Date, and Country of Origin fields are not included in this feature.
6. The number placed in the field will be pulled from a normal Oracle sequence and should be at least 6 digits long. The value loaded into the license plate will be padded with leading zeros to make the length of the minimum and maximum values equal. For example if the min = 1 and the max = 100000, the numbers generated will be 000001, 000002, etc.
7. The maximum value that can be used is 999,999,999.
8. If the maximum is reached, the Oracle counter will restart at the minimum value.
9. Item level sequences will override customer level sequences.
10. For Lot processing, AutoSeq is the same as selecting Y-Upon Receipt, except that minimum and maximum sequence numbers are required for auto-sequencing.
11. For serial number, User 1, 2 and 3, the Synapse processing after the plate is created will be the same as the Y option.

Add'l Capture

ASN Capture

ASN Capture Radio Buttons are available for Serial #, User 1, User 2 and User 3 with 2 options; Yes and No.

If an option is Yes, this information will not be recorded on the LP but in separate ASN capture tables. These tables will then be checked at picking to verify that inventory with the appropriate serial # or user-defined field had been received.

This option needs to be set prior to any inventory being received. If inventory currently exists when this option is activated, that inventory will not be allocated for outbound orders.

Note: This processing is not to be confused with receipts that are EDI transmitted via ASN transactions to simplify receiving via the RF ASN Receiving option 12.

1-Step Receiving with ASN Capture

When executing the 1-Step Receipt function for items that require ASN capture, note the following:

1. If any item has both required and ASN capture set for a field (serial number or user items 1 thru 3), the required option takes precedence and ASN capture is ignored.
2. After all non-ASN capture data has been entered for a plate, the prompts for the ASN capture fields are displayed beneath the existing data and the operator then repeatedly enters the ASN capture data. These are the only enterable fields.
3. The data is not stored in the plate but is saved in another table. The operator may exit entry of the ASN capture fields early and the plate will be updated accordingly.

ASN Capture Duplicate Checking

The following rules are used for duplicate checking when ASN capture data is being entered. There must be a format validation rule for the item and the rule must not allow for duplicates.

1. If an unshipped shipping plate exists – prohibit
2. If an inventory LP exists (returns plate) – prohibit
3. If there is receipt history for the same receipt order – prohibit
4. If there is receipt history for a different receipt - warning

ASN Capture Duplicate Checking with Do qty 1 LPs

ASN capture can also be mixed with "Do qty 1 LPs?" processing. There must be a format validation rule for the item and the rule must not allow for duplicates. When executing picking functions for items that require ASN capture, note the following:

1. If unshipped shipping plate exists – prohibit
2. If inventory LP exists (returns plate) – prohibit
3. There will be a warning message if the value was never received

RF Screen Label

The RF display label can be specified for Lot #, Serial #, User 1, 2 or 3. If no screen label is specified, the default value will be used for RF display.

Special 20 Character Entry Setup

1-Step Receipt (option 11) allows the entry of a 20 character User 3. If the RF Screen Label for User 3 begins with a plus sign (+) then the entire width of the RF screen (20 characters) is available up for data entry. If there is available space on the screen, the line immediately above will contain a prompt surrounded by dashes (<--- ... --->) where ... is replaced with the final 4 characters of the RF Screen Label for User 3 – if there are no characters then UITM3 is used.

Use Catch Weight

This setting determines whether catch weights apply to this item. The values are:

- Yes – Item has catch weights.
- No – Item does not have catch weights.

Outbound Catch Weight

This parameter determines the type of outbound catch weight captured an item. The options are:

- Blank - No outbound capture is required.
- G – Gross weight entry is required.
- N – Net weight entry is required.

If Use Catch Weight is set to No (or blank), then Outbound Catch Weight is ignored.


Capture Pick UOM

This allows the Serial Number Capture/Tracking to be by pick unit of measure, not the base unit of measure. For example, if the base unit of measure is each and a case is picked, the serial number is tracked for the case.

Inbound Catch Weight

Synapse assumes that catch weight being captured during receiving is gross weight. If this setting is Net, the system will take the quantity multiplied by the Tare weight and add the results to the weight entered by the operator; qty * tare = y, y + catch weight entry = plate entry.

Item Specs/Receiving/Options – 2



Do NOT allow the receipt of damaged product

If this option is selected, LIP's that have the Damaged inventory status (DM) cannot be received. If no value is selected or the Use Default option is selected where applicable, SYNAPSE will default to the value displayed in the Default box.

Returns Disposition

This is the category for returns. This data is maintained in the 'ReturnsDisposition' validation table. If no value is selected or the Use Default option is selected where applicable, SYNAPSE will default to the value displayed in the Customer Default box.

Default Receiving Status

This is the default status that appears in 1-Step Receiving and will save the RF operator keystrokes if the appropriate value is entered here.

Note: If there is no value in this field, the receiving process populates the field with the first included inventory status value from the order detail line, otherwise it will use “AV” (Available).

Putaway Confirmation Method

This entry determines the RF entry information required at putaway.

- Location, Item, Quantity
- Location, Quantity

If no value is selected or the “Use Default” option is selected where applicable, SYNAPSE will default to the value displayed in the Default box.

Single-Quantity License Plates

- Yes - All license plates will have a quantity of 1. This prevents you from creating a LiP in a quantity greater than 1 when receiving a product (via receiving, returns or inventory load) that requires data capture and specifies no duplicates. It also affects processing that allows the quantity of a LiP to be changed. This would most commonly be used for an item that requires unique serial numbers.
- No - License plates can have a quantity > 1

Note: If the item is set to a Max qty 1, then the unit of measure must be the base unit of measure.

If no value is selected or the “Use Default” option is selected where applicable, SYNAPSE will default to the value displayed in the Default: box.

RF screens that are affected by this setting include:

- Phys Inventory - option 36
- Location Load - option 91
- Work order - option 61
- Inv Adjustment - option 81
- Detail Return - option 18
- Damaged Items - option 96
- Cycle Count - option 35
- Build Pallet - option 13
- Dekitting – option 64
- 1-Step Receipt - option 11

CRT-based processing affected by this setting includes:

- Inventory Adjustment
- Receive Load
- Returns

Parse Field Entry

The Purpose of the parse field entry is to scan a serial #, lot #, user 1, 2, or 3 and parse all or part of a value into another field. The original field value is kept in the scanned field. For example, the first 6 characters of the lot number is also the manufacturing date. By setting up the lot number as the input field and the manufacturing date as the parsed field, the entire lot value will be kept in the lot number field and the first 6 characters are extracted and put in the manufacturing date field. To set a rule:

- Double click on the Rule field and select a rule from a list. Note: The rules are created in Setup/Parsing Rules.
- Select the Entry Field for the rule from the pull down list.
- Set the Parse Rule Action Radio button to Yes.

If no parsing rule is selected for the item, the customer default is used. See the Setup/Parse Rules in the User Manual Documentation for an explanation of the parse rules.

Putaway Highest Whole UOM

When you receive an item you specify the unit of measure (UOM) you are receiving and normally this is the UOM that the putaway process uses when scanning the Putaway Profiles. If this flag is set, then the putaway process converts the base UOM and quantity to the highest whole UOM for the item. The highest whole UOM is then used to scan the Putaway Profiles. For example, if this option is selected, if you receive 100 cases of an item and there are 100 cases on a pallet (highest whole UOM), then the pallet UOM will be used to search the Putaway Profiles and find a warehouse location.

LP Creation Controls

Disallow Mixing with other items

If you check this box, other items can't be mixed on a plate with this item.

Disallow overbuilt LPs

When this option is checked, the application uses the Pallet Definition on the Item Specs/UOM tab to validate the quantity being added to the LiP. A “Can't over recv” message appears on the RF screen if you attempt to receive a quantity on a LiP that is greater than the Pallet Definition quantity.

Warn on LP's less than

Check this box to display a warning during receiving that this plate is less than the quantity entered in the displayed field.

Item Specs/Receiving/Instructions



This screen provides a free-form text area for adding item-specific receiving instructions to be shown on the RF terminal at receiving.

In most installations, the RF display screen is limited to a width of approximately 20 characters. The following rules apply for display of the free-form text area entered via the CRT on the RF displays:

1. A word (contiguous sequence of non-blank characters) will not be split across multiple lines unless the word is longer than the width of the screen.
2. All blanks at the beginning of a line (i.e. left edge of the screen) are removed.
3. All non-printable characters (e.g. carriage return, tab) are replaced by a single blank.
4. Any contiguous sequence of blanks is replaced by a single blank.

Automatically display instructions when handling

If ‘Automatically display instructions when handling’ is checked, the instructions automatically display on the RF. If the box is not checked, the “*” displays and the RF operator can view the instructions by using a function key.

Item Specs/Receiving/Format Validation

The screenshot shows a software interface titled "Customer INA - Item Maintenance for PEANUT TAFFY". The main menu bar includes "Item Specs", "Aliases", "Storage", "Substitutes", "Pick Fronts", and "Facility Settings". Below the menu is a toolbar with various icons. The top navigation bar has tabs: "Name", "UOM", "Specs", "Receiving" (which is selected), "Shipping", "Labeling", "Hazardous", and "Handling". Underneath these are two groups of tabs: "Options - 1" and "Options - 2", followed by "Instructions" and "Format Validation" (which is also selected). The main content area is titled "Format Validation" and contains a table with five rows, each representing a validation rule for different fields: Lot #, Serial #, Color, User 2, and User 3. Each row has a "Rule" column (containing the field name) and an "Action" column (containing a dropdown menu). The "Action" dropdowns show the following settings:

Rule	Action
Lot #:	SAPUTOLOT Prohibit W - Warn
Serial #:	 CustDefault W - Warn
Color:	 CustDefault W - Warn
User 2:	 CustDefault W - Warn
User 3:	 CustDefault W - Warn

At the bottom of the window, a status bar displays "LINUX2TEST Facility ZET (Last Update by ANN at 10/29/2013 9:43:15 AM)".

Rule

Format validation rules can be chosen for Lot #, Serial #, User 1, 2 or 3. These can be set so that the data is validated upon entry, i.e., accept only numeric characters, the entry must have 10 characters, etc. These rules are maintained via the Setup/Format Validation Rules Screen. See the User Manual Documentation for an explanation of the rules. CRT and RF entries are validated against these rules.


Action

An Action is specified for each rule:

- Warn – Warns you that the data does not comply with the format validation for the field.
- Prohibit - Prohibits you from making an entry that does not comply with format validation for the field.
- CustDefault – The customer setup default will be used.

Item Specs/Shipping

Item Specs/Shipping/Options – 1



Back Order Policy

This defines the Default Backorder policy for this item. This can be overridden at the order-line level. Valid Back Order Status Codes:

Value	Normal Processing	Abbreviation
A	Backorder the entire line item – Do not pick the line short. This option cancels the line item at wave release and creates a new order with the exact same line item.	BackOrderAll
N	No Backorder - Ship Short - No backorder is created at load close.	NoBackOrder
P	Ship Available- Backorder is created for the shortage at load close	BackOrdrPart

Value	Normal Processing	Abbreviation
W	Await CSR – Works in conjunction with the Backorder CSR Email option. When a shortage occurs at wave release, processing will stop for the order, an internal flag will be set for the order and any tasks created will be deleted. A Ship Short button will appear on the order. When clicked, the order will process as if the “N” (No Backorder) policy is in effect.	AwaitCSR
X	Cancel the line item at wave release.	Cancel
C	SYNAPSE will default to the value displayed in the Default box.	Customer Default

These values work in coordination with the “Reject short orders and allow resubmission” check box on the Customer/Shipping/ Options – 2 screen. If this box is checked, a short order is cancelled upon commitment, regardless of the back order policy of any of the line items.

This processing is slightly altered for Material Issue generated orders. See additional documentation associated with this process.

Allow Substitution

This radio button allows item substitution processing to be turned off or on at the item level. Item substitutes are defined at the item level on the Item Maintenance/Substitutes screen.

If no value is selected or the “Use Default” option is selected where applicable, SYNAPSE will use the value displayed as the Default.

Default Inventory Status Selection

This data is required for the addition of a new item. The item-level default inventory status code (it can be single or multiple status codes) for inventory that is allowed to be shipped is set here. These values are set up in the InventoryStatus validation table.

If no value is selected or the “Use Default” option is selected where applicable, SYNAPSE will default to the value displayed in the Default box.

Default Inventory Class Selection

This data is required for the addition of a new item. The item-level default inventory class code (it can be single or multiple class codes) for inventory that is allowed to be shipped is set here. These values are set up in the InventoryClass validation table.

In order to associate a list of valid Inventory Class values with a customer/item, there **must** be a validation table named “class_to_company_ZZZ” where the suffix (ZZZ) is the Customer ID. Otherwise, the available values for inventory class selection default to the InventoryClass validation table.

If “class_to_company_ZZZ” is setup, and the customer ID is entered on the following screens, the criteria selection will be restricted to the values valid for the customer.

- Lookup/License Plate Information
- Lookup/Shipping Plate Information
- Inventory Class lookup,
- Return Order Lookup

Additionally, the Customer/Shipping/Options1 screen will restrict the choice of Default Inventory Class Selection based on the “class_to_company_ZZZ” table.

If no value is selected or the “Use Default” option is selected where applicable, SYNAPSE will default to the value displayed in the Default box.

See the section in this manual on Miscellaneous Setup Topics for additional information.

FIFO Processing

This setting determines the FIFO window the operator can use to override a suggested pick.

- Enabled - When this is selected, a value needs to be set in the FIFO Window Days field. Strict enforcement – The operator will not be allowed to pick inventory outside of the FIFO date. Requests for alternate picks will only be created with inventory for the FIFO date.
- Disabled - When this is selected, no FIFO is enforced. When an operator picks an item allocated by FIFO, he will be allowed to override the pick or request an alternate pick for any allowable inventory for the item.

FIFO Window Days

Valid values are 1 –999. When the operator overrides a pick or requests an alternate pick, this value represents the number of days the system will allow the alternate inventory FIFO date to be in relation to the FIFO date of the inventory in the original pick.

This logic is also in effect for LIFO.

Item Specs/Shipping/Options – 2

Shipment Order Quantity Type

This value is the default used when an outbound order is created. System supported values are:

- Exact – The system will attempt to fill the order with the exact amount ordered. This is normally for all items ordered by a defined unit of measure, such as case or each.
- Approximate – The system will attempt to fill the order within the % variance entered in the Acceptable Pick Range field. This is usually for items ordered by weight such as raw materials.
- Customer Default - SYNPASE will default to the value displayed in the Default box.

Weight Check Required

- Yes – Manual weight checking is required prior to order loading.
- No – Manual weight checking is not required.

If no value is selected or the “Use Default” option is selected where applicable, SYNPASE will default to the value displayed in the Default box.

LiP Substitution Reason Required

- Yes – During picking, if a LP is specified and substituted, the RF operator must enter the LiP Substitution reason. The operator uses a process similar to the “Can’t Pick” in picking and the reason codes available are from the “CantPickReasons” validation table. The RF operator must use the F6 key to enter the reason code when substituting.
- No – Lip Substitution Reason is not required.

If no value is selected or the “Use Default” option is selected where applicable, SYNAPSE will default to the value displayed in the Default box.

Transportation UOM

This field is used for an interface with the Transynd Transportation Management System. Please contact the TSD at Zethcon for further information.

SIP Carton UOM

This field is used for an interface with the SIP processing. Please contact the TSD at Zethcon for further information.

Track Picked Pick Front Plates

Checking this option will allow the tracking of the lot numbers from not only pick fronts but also Totes and Multi-plates on the Shipping Plate.

Minimum Ordered Units/ Multiple Ordered Units

These settings control a scenario where an item contains more than one piece inside a case and the case is never to be broken (such as 2 bottles in a case).

During outbound order entry, when the item is being entered, the system will validate the quantity to ensure the ‘minimum’ ordered quantity is met. If it is not, the system will warn you that the quantity must be changed. The system will also validate the quantity to ensure the ‘multiple’ ordered quantity is met. If it is not, the system will warn you that the quantity must be changed.

If these fields are left blank, the default value is used.


Minimum Ordered Units

The Minimum Ordered Units defines what the minimum ordered quantity can be on any outbound order (it does not apply to the inbound quantity).

Multiple Ordered Units

The Multiple Ordered Units defines in what multiples the ordered quantity can be. For example, if there are two bottles (eaches) in a case and the minimum ordered quantity is 2 eaches, the Multiple Ordered Unit may be 2 eaches since these should be ordered in multiples of 2 (4, 6, 8...).

Item Specs/Shipping/Ship To Expiration




This functionality allows shipments to certain consignees to pull from “fresher” product than shipments to other consignees. A customer level checkbox, “Allow outbound entry of minimum days to expire” must be checked in order for this sub tab to be visible. The checkbox is found on the Customer/Shipping/Options-2 tab.

The functionality is invoked upon order import or entry. When an order with the item is shipping to a consignee with values configured for the item, the appropriate value for the Minimum Days to Expiration will be automatically populated in that field on the Order Item Info screen.

For orders with items having entries in the Minimum Days to Expiration field, commitment will occur differently from those that don't. As the system commits inventory for these qualifying orders, it will narrow the inventory that is available to commit by excluding inventory that has expiration dates that are not at least equal to today's date plus the Min Days value for the line being committed. Any inventory whose expiration date is sooner than the Min Days value will not be committed. If the user wishes to commit ignored inventory, he may remove the Minimum Days to Expiration value from the detail record of the appropriate line of the order.

Item Specs/Shipping/Instructions



This screen is used to enter free-form outbound shipping instructions text to display on the RF terminal during the shipping process. These instructions can be specific to a consignee.

If “Automatically display instructions when handling” is checked, the RF operator will have the instructions automatically displayed. If the box isn’t checked, an “*” will be displayed and the RF operator can view the instructions by using a function key.

In most installations, the RF display screen is limited to a width of approximately 20 characters. The following rules apply for display of the free-form text area entered via the CRT on the RF displays:

1. A word (contiguous sequence of non-blank characters) will not be split across multiple lines unless the word is longer than the width of the screen.
2. All blanks at the beginning of a line (i.e. left edge of the screen) are removed.
3. All non-printable characters (e.g. carriage return, tab) are replaced by a single blank.
4. Any contiguous sequence of blanks is replaced by a single blank.

Item Specs/Shipping/BOL Comments

This screenshot shows the 'Customer INA - Item Maintenance for APPLE' application. The main menu bar includes 'File', 'Edit', 'View', 'Setup', 'Customer...', 'Print', 'Help', and 'Exit'. Below the menu is a toolbar with icons for back, forward, search, and other functions. The top navigation bar has tabs for 'Item Specs', 'Aliases', 'Storage', 'Substitutes', 'Pick Fronts', 'Facility Settings', 'Name', 'UOM', 'Specs', 'Receiving', 'Shipping' (which is selected), 'Labeling', 'Hazardous', and 'Handling'. A sub-navigation bar below shows 'Options - 1', 'Options - 2', 'Ship To Expiration', 'Instructions', and 'BOL Comments' (which is selected). The main area contains a 'Consignee:' field with '0031' entered, a list of icons for managing consignees, and a text area with the instruction 'Call Consignee on day of delivery at 888-976-3123.' followed by a small text input field. At the bottom, it says 'Last Update by at' and 'LINUX2TEST Facility ZET (Last Update by SWINCHELL at 4/8/2013 11:04:39 AM)'.

This screen is used to define free-form text outbound instructions to be printed on the Bill of Lading (BOL) during the shipping process. These instructions can be specific to a consignee.

Item Specs/Labeling

Item/Specs/Labeling/General

This screenshot shows the same 'Customer INA - Item Maintenance for APPLE' application. The top navigation bar and sub-navigation bar are identical to the previous screenshot. The main area now displays a table under the 'Labeling' tab. The table has columns for 'Consignee', 'Label Profile', 'Last User', and 'Last Update'. One row is visible with '0031' in the Consignee column, 'BLP' in the Label Profile column, 'ANN' in the Last User column, and '10/30/2013 11:30:15 AM' in the Last Update column. At the bottom, it says 'LINUX2TEST Facility ZET (Last Update by SWINCHELL at 4/8/2013 11:04:39 AM)'.

Entries on this screen associate an item or item/consignee combination with a specific label profile for the printing of output labels.


Consignee

The consignee information must first be entered on the Setup/Consignee Maintenance screen and then be associated with this customer on the Setup/Customer/Shipping/Options –1 tab. This field is optional.

Label Profile

Choose this value from the label profiles defined on the Setup/Label Profile screen.

Item/Specs/Labeling/Labeling Options



This screen is used as part of the optional automatic lip label generation in the Transloading process. It provides functionality to produce a label upon the arrival of an Inbound Customer load. The label is created in labeling software (Nicelabel). The label produced is essentially a license plate containing a significant amount of human readable and bar coded information, such as PO, item number, etc. This is also referred to as Front End Labeling (FEL).

If no options are selected or the Default options are selected, the system will use the Default field values.

Print Plates on Load Arrival

Checking this box will trigger the label creation at the beginning of 1-Step Receiving.

System Generated Plates

Checking this box will trigger the label creation after the item is received in 1-Step Receiving. Generating the labels after receipt has the potential to add more specific information on the label.

Label Profile for Plate Printing:

Select the appropriate Label Profile. These are defined on the Setup/Label Profile/Label Profile Maintenance Screen.

Default Handling Type:

Select the Default Handling Type for the receipt. These values are set up using the Setup/Handling Type/Receipt Handling Types Definition screen.

SSCC Options**Order Header Field that contains Manufacturer UCC Code**


This is used by specific labeling procedures to identify the Manufacturer UCC code from an order header field and not from the code identified on the Customer/Name tab.

Casepack From Uom/Casepack To Uom

These fields are used to determine how to obtain the casepack quantity when producing SSCC labels. Item values will override customer-level values. If no values are present, the defaults are PCS and CTN.

Item Specs/Hazardous

Item Specs/Hazardous/DOT



Hazardous Material

Check this box if the item is hazardous. The item will display with a yellow background color on various grids on the CRT. This data is used to automatically supply information to the RF operator handling the item.

The Hazardous symbol appears on the Item Specs tab if an item is set as Hazardous.

Note: If the Hazardous Material box is not checked, and there is data on this screen for the RF operator, the information will still be automatically shown to the RF operator.

Hazard Class for Storage

One Hazard Class code can be entered for the item. These codes are maintained in the "HazardousClasses" validation table.

Chemical Codes - Primary, Secondary, Tertiary, Quaternary

Up to four chemical codes can be entered for each transportation mode. The RF Chemical code displayed will reflect the transportation mode for the outbound order.

- DOT – Department of Transportation (Truck/Rail/Other)
- IMO – International Maritime Organization (Sea)
- IATA – International Air Transport Association (Air)

The codes are maintained for the installation on the Setup/Chemical Codes screen.

Material Safety Data Sheet Format

This field defines the directory path and name for the PDF version of the Material Safety Data Sheet (MSDS) for this item.

View this MSDS

Use this button to view the MSDS entry defined above. Adobe® Reader Version 7 or higher must be installed on the same server as Synapse.

20 MULE TEAM

Firebrake® 500

Material Safety Data Sheet
DATE OF ISSUE September 2004
Supersedes April 2002 Version

1 | Chemical product and company identification

Product name:	Firebrake 500
Grade:	All
Product use:	Flame retardant
Chemical formula:	2ZnO·3B ₂ O ₃
Chemical name/synonyms:	Anhydrous Zinc borate
Chemical family:	Inorganic borates
CAS registry number:	12767-90-7

(Refer to Section 15 for TSCA/DSL Chemical inventory listing)

MANUFACTURER:
U.S. Borax Inc.
26877 Tourney Road
Valencia, CA 91355-1847

EMERGENCY PHONE NUMBERS:
24 Hr. Medical Info. Service ... (661) 234-5200
Chemtrec (Spills): (800) 234-9300

Print MSDS at Load Close

Check this box to have the MSDS document print at load close for this item.

Item Specs/Hazardous/SARA

Customer INA - Item Maintenance for APPLE

Item Specs		Aliases		Storage		Substitutes		Pick Fronts		Facility Settings		< > +		Customer...			
Name	UOM	Specs	Receiving	Shipping	Labeling	Hazardous	Handling										
DOT		SARA															
Product Type <input type="checkbox"/> Gas <input type="checkbox"/> Mixture <input type="checkbox"/> Liquid <input type="checkbox"/> Pure <input checked="" type="checkbox"/> Solid		Hazard Class <input type="checkbox"/> Delayed (chronic) <input type="checkbox"/> Immediate (acute) <input type="checkbox"/> Fire <input checked="" type="checkbox"/> Reactivity <input type="checkbox"/> Sudden release of pressure		Container Type Container: Plastic drum		Pressure:		Temperature:									
Percentages														<input type="checkbox"/> Trade Secret			
CAS 1	ZINC	Percentages		CAS 11	Percentages												
CAS 2	94279-65-9	50		CAS 12													
CAS 3	1317-34-600	40		CAS 13													
CAS 4		10		CAS 14													
CAS 5				CAS 15													
CAS 6				CAS 16													
CAS 7				CAS 17													
CAS 8				CAS 18													
CAS 9				CAS 19													
CAS 10				CAS 20													

LINUX2TEST Facility ZET (Last Update by ANN at 10/30/2013 12:53:55 PM)

Item characteristics can be maintained for any facility storing materials qualifying for reporting under SARA (Superfund Amendments and Reauthorization Act) reporting requirements.

Product Type

One or multiple Product Type characteristics can be selected here.

Hazard Class

One or multiple Hazard Class characteristics can be selected here.

Container Type

Container

One Container code can be entered for the item. These codes are maintained in the “ContainerTypes” validation table.

Pressure

One Pressure code can be entered for the item. These codes are maintained in the “SARAPressures” validation table.

Temperature

One Temperature code can be entered for the item. These codes are maintained in the “SARATemperatures” validation table.

Percentages

CAS Number

The codes are maintained for the installation on the Setup/CAS Numbers screen. These are unique numbers that identify chemicals.


Percentages

These are the percentages of each chemical (CAS). The values entered here must total 100.

Trade Secret

This identifies the information as a trade secret. This is used for reporting purposes.

Item Specs/Handling



This configuration is designed to allow inventory to automatically change inventory status when inventory is moved into and removed from certain location types.

Once all necessary settings are made to enable the functionality, product moved into a location with the specified location type will be automatically adjusted to the inventory status configured as the Entering status. Later, when the product is moved out of the location, it will be automatically adjusted again, this time to the Exiting inventory status.

1. These adjustments will normally occur via RF moves or inventory moves performed through the Aggregate Inventory Re-warehousing screen.
2. Inventory adjustments for a location will trigger the functionality but can be avoided by adding “IA” as an excluded task.
3. Should a mixed pallet containing both product configured and product not configured for the functionality be moved into a location of the defined type for the configured item, only the configured item will be adjusted. When the adjustment is made, the Adjustment Reason will be recorded per the setup of the Reason mentioned above.
4. Each of these movements will be associated with a corresponding Business Event. “ENTR” for the Entering Auto Adjust and “EXIT” for the Exiting Auto Adjust.
5. When triggered, the adjustment occurs and if an event is configured, it will create a Misc. Order associated with the charge. As long as that Misc. Order is not processed, additional charges will accumulate against the same Misc. Order.

Location Type:

Use the drop down box to select a location type. This is the type of location that will be used to trigger the status change.

Exclude Task Types

This field allows for a comma-delimited list of task types that should **not** generate an adjustment or event.


Inventory Status - Upon Entry/Upon Exit

Enter the Inventory Status to update the entering/exiting inventory.

Adjustment Reason - Upon Entry/Upon Exit

Enter the Adjustment Reason code for the Entry/Exit inventory adjustment transaction.

Item/Aliases



An item alias must be unique for the customer. It is typically used to link the UPC code to the item code scanned during RF processing or CRT-attached scanning.

1. Maximum length for an alias is 16 characters.
2. For UPC codes to be recognized the description should be “UPC”.
3. Items may have multiple alias codes.
4. The RF entry length for Item or Alias is 16 characters. If a customer requires an item ID greater than 16 characters and less than 21 characters, the Item Alias processing needs to be used for the RF entry.
5. If a Partial Match is allowed, this field should be set to Y. Alias Partial Match allows a partial match of the item alias instead of requiring an exact match.

Item/Storage

Customer INA - Item Maintenance for APPLE

Item Specs	Aliases	Storage	Substitutes	Pick Fronts	Facility Settings	Buttons							Customer...																												
UOM Sequence:	10	UOS Sequence:	10								Buttons																														
UOM:	Pallet	Unit of Storage:	2 DEEP	UOM in UOS:	4								Buttons																												
<table border="1"> <thead> <tr> <th>UOM Sequence</th> <th>UOM</th> <th>UOS Sequence</th> <th>UOS</th> <th>UOM in UOS</th> <th>Last User</th> <th>Last Update</th> </tr> </thead> <tbody> <tr> <td>10</td> <td>Pallet</td> <td>10</td> <td>2 DEEP</td> <td>4</td> <td>ANN</td> <td>10/30/2013 3:48:26 PM</td> </tr> <tr> <td>20</td> <td>Pallet</td> <td>20</td> <td>4 DEEP</td> <td>8</td> <td>ANN</td> <td>10/30/2013 3:49:01 PM</td> </tr> <tr> <td>30</td> <td>Pallet</td> <td>30</td> <td>5 DEEP</td> <td>10</td> <td>ANN</td> <td>10/30/2013 3:49:37 PM</td> </tr> </tbody> </table>														UOM Sequence	UOM	UOS Sequence	UOS	UOM in UOS	Last User	Last Update	10	Pallet	10	2 DEEP	4	ANN	10/30/2013 3:48:26 PM	20	Pallet	20	4 DEEP	8	ANN	10/30/2013 3:49:01 PM	30	Pallet	30	5 DEEP	10	ANN	10/30/2013 3:49:37 PM
UOM Sequence	UOM	UOS Sequence	UOS	UOM in UOS	Last User	Last Update																																			
10	Pallet	10	2 DEEP	4	ANN	10/30/2013 3:48:26 PM																																			
20	Pallet	20	4 DEEP	8	ANN	10/30/2013 3:49:01 PM																																			
30	Pallet	30	5 DEEP	10	ANN	10/30/2013 3:49:37 PM																																			
LINUX2TEST Facility ZET (Last Update by ANN at 10/30/2013 12:53:55 PM)																																									

The screen defines what quantity of a specific unit of measure of the item will fit into a specific unit of storage.

The size of a storage location is defined by associating the location with a Unit of Storage. The actual dimensions (height, weight, depth, weight limit) of the Unit of Storage are defined in the Setup/Facility/Location/Units of Storage screen. If putaway uses the UOS method, this must be defined for optimal results.

UOM Sequence -- UOS Sequence

This is the sequence for the unit of measure/unit of storage combination being defined.

UOM

This is the unit that will be stored in the UOS, i.e., pallet, case, box, etc.


Unit of Storage

This is the UOS. These are set up in Facility/Locations/Units of Storage.

UOM in UOS

Enter the quantity of the UOM that will fit into the UOS.

Item/Substitutes



If item substitution is allowed (the radio button is set on the Item Specs/Shipping/Options-1 tab), the substitute item IDs and search sequence are defined here.

Once a substitute is defined for an item, the system will allocate that item in lieu of the ordered item when the ordered item is out of stock. The process is transparent to the picker but is reflected on the order - the Item on the order will show what was shipped and the Ordered Item will show what was ordered. During setup, the CSR should make sure there won't be an issue with labeling and/or EDI as the data may or may not be setup with support for item substitution in those areas.

Item/Pick Fronts

The screenshot shows the 'Customer INA - Item Maintenance for APPLE' application interface. The 'Pick Fronts' tab is selected. The facility is set to 'ZET'. A pick front named 'PL009' is defined with a pick UOM of 'Case' and a replenish UOM of 'Pallet'. The minimum quantity is 1, top off quantity is 1, and maximum quantity is 2. The status shows the last picked date as 10/21/2013 11:32:53 AM. A table at the bottom lists the configuration details:

Facility	Pick Front	Pick UOM	Minimum Qty.	Minimum UOM	Replenish With UOM	Maximum Qty.	Maximum UOM	Last User	Last Update
ZET	PL009	Case	1	Pallet	Pallet	2	Pallet	ANN	10/21/2013 9:41:24 AM

LINUX2TEST Facility ZET (Last Update by ANN at 10/30/2013 12:53:55 PM)

There are 2 kinds of pick fronts; static and dynamic. The setup described below is for Static Pick Fronts. Please see Chapter 53 of the User Manual for information on Dynamic Pick Fronts.

Facility

To support processing items in multiple facilities, pick front definitions are specific to a facility. You must have access to the facility and be working “in the facility” to select the facility code.

Like most other locations, a pick front has a limited capacity. Because of this, additional inventory must periodically be delivered to the pick front to meet picking requirements. This process of re-stocking is called replenishment.

An item may have more than one pick front in a facility for the same UOM. When assigning pick tasks, the system will select the pick front with the least pending tasks.

Pick Front

This must be an existing location with a location type of PF (pick front). Pick Fronts are also called Forward Pick Locations in some screens.

For active pick fronts this field is filled in. If the item does not currently have an active pick front, this will be blank.

Pick UOM

Enter the UOM of the item to be picked from this pick front. There should be a separate entry for each separate UOM to be picked from this pick front for the item.

Replenish With UOM

Enter the UOM for the item for replenishment. This can be the same as the pick UOM or it could be a larger UOM. For example, an each in a pick front could be replenished with cases of the same item.

Use Existing Plates

This setting is for a customer that must use the same plate for the outbound as the receipt plate. Tasks are generated, the user picks to this plate and to a shipping plate. It is not widely used.

Minimum UOM and Quantity

This is the minimum quantity for the pick front. If the inventory drops below the minimum, a replenishment task will be created if there are no other pending replenishment tasks. The minimum must be set above 0 for replenishment tasks to be generated.

Top Off UOM and Quantity


Top-off replenishment is used to refill pick fronts during slower processing periods of the day. This value indicates the minimum quantity for a top-off task.

Top-off replenishments are requested via RF function 83. The quantity field must have a value greater than 0, even if Top-off processing is not being used.

Maximum UOM and Quantity

Enter the maximum quantity for the pick front. Replenishment tasks should not be generated to allow more inventory than the pick front maximum.

Request Replenishment Button

Clicking  creates a Top-Off replenishment request for the pick front.

Whole Units Only

When checked, the "Whole Units Only" box informs the Replenishment process that only Full picks should be generated when the Top-Off is requested via the Replenish button.

This field is NOT on the database. It is an option on the screen just used at the time of the request. The system does not save this setting for each item.

System Generated

This option is used for Dynamic Pick Front processing. The system will not allow both static and dynamic pick fronts for the same facility, customer id, item and pick UOM combination.

Trace this Request

The Replenishment area contains a "Trace this request" checkbox. If the box is checked prior to the replenishment Top-Off request, the system will generate trace messages (which will appear

on the Messages Form under type T - Trace Message). The checkbox will only appear on the screen if the user has Supervisor security, since these checkboxes are intended to be used for support/debugging purposes.

Last Picked Date

Informational Only.

Item/Facility Settings

Facility	Putaway Profile	Allocation Rule	Replenishment Allocation Rule
ZET	C - Use Default	ALL-all	REPL-PAL-PALLET

Facility	Default Putaway Profile	Default Allocation Rule	Default Replenishment Allocation Rule
ZET	BP-BP	ALL-all	REPL-repl

LINUX2TEST Facility ZET (Last Update by ANN at 10/30/2013 12:53:55 PM)

To support customer processing in multiple facilities within the same installation of SYNPASE, these values for customer defaults are selected here by facility.

Note: The operator must be in the corresponding facility to make changes. Use the right click Change Facility option. To add an entry, use the insert record button **+** on the lower tool bar.

If no value is selected or the “Use Default” option is selected where applicable, SYNPASE will default to the value displayed in the Defaults box.

Allocation Rule

The item allocation rule is set here. This is selected from the facility list entered using the Setup/Facility/Allocation Rules Screen.

Each UOM to be ordered for an outbound order must have a corresponding entry on an allocation rule attached to the item. The system will attempt to follow the allocation rule before allocating other inventory that does not fit the rule. If there is no allocation rule for the UOM, the system will not generate pick tasks.

Replenishment Allocation Rule

The item replenishment allocation rule is set here. This is selected from the facility list entered using the Setup/Facility/Allocation Rules Screen.

Putaway Profile

The item Putaway Profile rule is set here. It determines the how the item will be put away in the warehouse. This is selected from the facility list entered using the Setup/Facility/Putaway Profiles Screen.

Facility Setup

Definition

It is important to understand the difference between a facility, a warehouse, and a campus in SYNPASE.

A **Facility** is a single center of inventory activity, usually a warehouse or part of a warehouse and its environs. All merchandise location and movement take place within the context of a facility, which must be specified to SYNPASE before any other computer events may occur.

A **Warehouse** is a single building that stores merchandise. It has no technical definition within SYNPASE.

A **Campus** is a cluster of facilities in close proximity. It is not a required entity in SYNPASE and used for installations with customers using multi-facility picking.

Facility/Facility Maintenance

Facility Maintenance/Name

The screenshot shows a Windows application window titled "Facility ZET - Zethcon Corporation". The window has a toolbar with buttons for Name, Remit to Address, Options, Scheduler, Utilization & Costs, and Tender. Below the toolbar, there are several input fields and dropdown menus:

- Facility:** ZET (Status: Active)
- Name:** Zethcon Corporation
- Address:** 512 Higgins Road
- City:** Park Ridge
- State/Province:** IL
- Postal Code:** 60068-5712
- Country:** USA
- Facility Manager:** Gail Russell
- Phone:** 847.318.0800
- FAX:** 847.318.0807
- E-Mail:** gail@zethcon.com
- General Ledger ID:** (empty)
- Campus:** TS TEST
- TMS Facility Group:** NCAL NCAL
- Surcharge Rategroup:** PST
- Order Completion Label:** (dropdown menu with edit icon)
- Label Profile:** (dropdown menu with edit icon)
- Printer:** (dropdown menu with edit icon)

At the bottom of the window, a status bar displays: LINUX2TEST Facility ZET (Last Update by JSTANCYK at 10/27/2013 9:26:21 PM).

Facility

The Facility ID must be unique for each facility. It is entered when a new facility is added, and cannot be changed.

Status

Values are maintained in the 'FacilityStatus' validation table.

- A – Active – The facility is in use.
- I – Inactive – The facility is not in use. No inventory movement should take place.

Name

This field contains the name of the facility. The field is required.

Address

This is the street address for the facility. The field is optional

City

This is the city of the facility. The field is optional.

State/Province

Values are maintained in the ‘StateOrProvince’ validation table. Leave this blank for countries outside the U.S. and Canada. The field is optional.

Postal Code

Proper formats are 99999 and 99999-9999. Values are not edited for proper format or for correspondence to the State/Province field. The field is optional.

Country

Values are maintained in the ‘CountryCodes’ validation table. The field is optional.

Order Completion Label

This configuration signals the dock/loaders that an order is complete. This works by generating a label automatically (not RF triggered specifically) when the order goes to Picked status. This would happen whenever the last pick, whether it is OP (order pick) or PK (pick task), is completed and is staged.

Label Profile

The Label Profile for the label generated automatically.

Printer

The designated printer for printing the label.

Facility Manager

This is the manager of the facility. This field is informational only and optional.

Phone

This is the primary contact phone number for the facility, usually the facility manager’s phone number. The field is informational only and optional. The field is not edited for format.

Fax

The field is informational only and optional. The field is not edited for format.

E-Mail

This is the primary e-mail address for the facility, usually the facility manager’s e-mail address. The field is informational only and optional. The field is not edited for format.

General Ledger ID

This field is informational only and optional. The field is not edited for any particular format.

Campus

This field identifies the facility as being part of a campus grouping of proximate facilities. Values are maintained in the ‘CampusIdentifiers’ validation table. The field is informational only and optional.

TMS Facility Group

This field is used to provide data to the TMS export file where applicable. Values are maintained in the ‘TMSFacilityGroup’ validation table. The field is optional.


Surcharge Rate Group

This is used for Canadian Tax processing.

Additional Buttons



- You can click this button to clone an existing facility. The Clone Facility window appears.



- Select the database that you want to copy the facility to – this field is optional.
- Type the a unique facility name in the New Facility ID field.
- Select the options that you want to Clone. You can use the **Select All** or **Select None** buttons.
- Click OK to clone the facility.

Facility Maintenance/Remit to Address

The Remit to Address can be used to have the facility's customers remit payments to a different address, such as the corporate accounting office. It can be used on invoices and other documents that use a remit-to address. The entire Remit to Address screen is optional.

Name

This field contains the name used for the remit-to address. This might be the facility name, or it might be a different entity, e.g., XYZ Corporate Accounting Office. The field is optional.

Address

This is the street address for the remit-to address. The field is optional.

City

This is the city of the remit-to address. The field is optional.

State/Province

Values are maintained in the 'StateOrProvince' validation table. Leave this blank for countries outside the U.S. and Canada. The field is optional.


Postal Code

Proper formats are 99999 and 99999-9999. Values are not edited for format or for correspondence to the State/Province field. The field is optional.

Country

Values are maintained in the ‘CountryCodes’ validation table. The field is optional.

Facility Maintenance/Options



Default Cross Dock Location

The field will be used as the cross-dock location for cross-docking processing.

When a new facility is added, the Default Cross Dock Location field is not validated against the existing locations. This allows you to enter the location before the locations are added for the facility. If you choose to enter the location, remember to define the location later when you get to the Setup / Facility / Location / Location Maintenance screen.

When you update an existing facility, the Default Cross Dock Location field is validated against the existing locations that have a location of type Cross Dock (CD). You must predefine the location on the Location Maintenance screen.

Enable Location Check ID

This is used to enable or disable the use of Check IDs. When enabled, RF operators may be required to enter a location’s Check ID when performing functions. When disabled, RF operators may be required to verify a location be rescanning or entering the location.

BOL Shipper Signature Bitmap

This is used as part of the VICS BOL processing. A signature bitmap file name and path can be added in this field and used to print on the Bill of Lading.

Cycle Count Item Summary

This is used to set up the summary function for Cycle Counting for the complete facility. The count will be by location not by LP. The items at a specific location will be totaled and the quantity will be entered along with the UOM. This setting is to be used with caution as it changes cycle counting for the facility. See the User Manual Chapter on Cycle Counting for more information about this option.

CHEP Identifier

A CHEP Customer ID field is available to specify a facility's CHEP customer ID that will be used on the CHEP export file. If blank, the system default value, "CHEPCUSTID", will be used when a CHEP export file is created.

Scanned LP Limit for Loading

This option provides the option to have a limit in the RF for the number of LP's that can be scanned for Loading before the user is required to drop the plates in the trailer. Once this number of LPs has been scanned, the RF user is requested to confirm loading the LPs – either the check ID or the location based on facility settings. A value of 0 or null implies not limit.

Restrict Putaway

Checking this box prohibits RF operators from overriding Directed Putaway. It applies to RF option 32 - Movement and option 97 – Putaway LP. When activated the system will only allow manual overrides to locations within the designated putaway zone(s) in the item's Putaway Profile. If the RF operator tries to put away an item in a location not in the putaway profile, the operator will receive a "Loc is restricted" message. This is specifically developed for facilities where the putaway location and zone is crucial to the inventory and environment such as HazMat inventory.

A restriction to this option is that all items in the facility must have a valid Putaway Profile with designated locations. If there is not a valid putaway profile the RF operator will not be able to put away the item. The operator will get the "Loc is restricted" message. At this point, you must uncheck this box in order for the putaway to continue.

Suppress LP in RF Loading

When you check this box for a facility, the license plate IDs will not display on RF Option 41- Dock Loading.

Yard Management

This box turns on the Yard Management function for this facility.

Days from Port

Enter the number of days from port in the field.


Include Weekends in Days from Port calculations

Check this box if the number of days from port includes weekends.

Pro Number by Facility Support


The lower grid is used to designate the geographical zone for a carrier for this facility. It is used for the automatic assignment of Pro numbers. Prior to assignment, the carrier/zone combination must be set up for the carrier. See additional information in this document regarding the automatic assignment of pro numbers under the Setup Carrier topic.

Facility Maintenance/Scheduler




These options allow you to set the facility work hours and the number of loads for both inbound and outbound activity. These fields work in conjunction with the Appointment Scheduler (Edit/Appointment Scheduler).

Facility Maintenance/Utilization



These settings are used as part of the Visual Warehouse option. Please contact the TSD for additional information.

Facility Maintenance/Tender



This screen allows you to specify a load tender map for a carrier for the facility.

LOCATION SETUP

Setup/Facility/Location/Location Maintenance

Facility ZET Location AA0101B

Location:	Status:	Description:
AA0101B	I In-Service	Storage Aisle AA
Check ID:	Aisle:	Section:
	AA	02
Location Type:	Aisle Level:	Velocity:
STO Storage	2	C Velocity C
Storage Type:	Aisle Side	Mixing Allowed:
FL Floor	<input type="radio"/> Left	<input checked="" type="checkbox"/> Customers
Equipment Profile:	<input type="radio"/> Right	<input checked="" type="checkbox"/> Items
AL All		<input checked="" type="checkbox"/> Lots
Unit of Storage:	Last Counted:	Weight Limit:
5D 5 DEEP	10/23/2013 10:20:00 AM	10000 Lbs.
Count After Pick?		Count Interval:
<input type="radio"/> Yes		0 Days
<input type="radio"/> No		Pick Count:
<input type="radio"/> Default: N		Drop Count:
LINUX2TEST Facility ZET (Last Update by ANN at 10/31/2013 11:52:57 AM)		

Location Maintenance/Definition

Location

The Location ID must be unique within each facility. It is entered when a new location is added, and cannot be changed. (You can delete an incorrect location ID, and reenter a new location if there is no inventory.) You can click the look-up button to access the Location Look-up screen.

Location IDs are usually assigned in one of two preferred formats:

1. Aisle/Bay/Level, with 1 or 2 letters or numbers for each part of the ID (e.g., 0101A)
2. Prefix + Sequence, with an alpha prefix that defines the type of location (e.g., DOOR14).

SYNAPSE has a Location Wizard (Setup / Wizards / Location Wizard) that can help you define a range of locations that begin with the same prefix, whether that is an aisle number or a mnemonic.

Note: Do not use a valid user ID as a location ID. When a license plate is being moved, the location of the license plate becomes the user ID. For recovery purposes the system knows that the plate was assigned to an operator rather than being in a valid location. If a user ID is also a location, the system may not process correctly.

Check ID

This is a 2-digit number that the operators must enter to confirm that a move or count is occurring at the proper location. SYNAPSE does not edit for a 2-digit entry. An alphanumeric scheme can be used, but digits are usually sufficient, and are easier for operators with handhelds to enter.

Check ID's are disabled for a facility if the Enable Location Check ID box is not checked on the Facility Maintenance/Options screen. This will result in all Check ID fields becoming read only and they will not be used in RF processing.

Standard rules for assigning check IDs are intended to make sure that an operator is unlikely to enter the right check ID at the wrong location:

1. Don't use the same check ID for any two contiguous locations – up, down, sideways, or diagonal. This includes the facing locations (across the same aisle) and the backing locations (directly behind).
2. Don't use the same check ID for two locations that are exactly one aisle apart in any direction. This lessens the chance of being in the wrong aisle and having SYNAPSE okay the operator's position at the right bay and level.

Location Type

This is the operational usage of the location. The field is required.

- CD – Cross Dock
- DEL – Inventory Deletion (Used only for Production Module)
- DOR – Door
- FPF – Flex Pick
- LOD – Load Location
- PF – Pick Front
- PND – Pick ‘N’ Drop
- SPC – Special
- SRT - Sortation
- STG – Staging Area
- STO - Storage
- USR – User
- XFR – Transfer Location (Used only for Production Module)
- YRD – Yard Location (Used for Yard Management)

Storage Type

Values are maintained in the ‘StorageTypes’ validation table. The field is required. It is used for informational purposes. The normal starter set is:

FL – Floor

NA – N/A

RK - Rack

Equipment Profile

Values are maintained in the ‘EquipmentProfiles’ validation table. The field is required. The value entered here is simply the name of an equipment profile, such as “High Rack” or “High Value” or “All”. You can define the profile details for each of these entries in the Equipment Profiles table, which is accessed from Setup / Equipment / Profiles from the SYNAPSE menu.

Unit of Storage

Values are maintained in the Units of Storage table, which is accessed on Setup/Facility/Location /Units Of Storage from the SYNAPSE menu. Typical values are PL – Pallet, BIN – Bin, FLOW – Flow, and RACK – Rack, 2D – 2 Deep. This value is used for UOS fit in putaway. The field is required.

Count After Pick?

- Yes - When an operator picks from a location, upon completing the pick, the operator will be redirected to the Cycle Count screen. The operator will perform a cycle count in the traditional manner with the exception that variances will result in a new cycle count task for the location rather than SUSPENSE balances. After the count is complete, the operator will be returned to pick task(s). If two operators are simultaneously picking from a location, only one user will be presented with the count task.
- No – Do not count a location after picking.
- Default - The default setting is based on the zone setting.

Status

This is the current condition of the location. The field is required.

- E – Empty (implies in-service)
- F – Full (implies in-service)
- I – In-Service
- O – Out-of-Service (abbrev: No Service)

For a new location, the status defaults to E – Empty but you can override the status on the screen.

Additional Status Information:

1. The In-Service/Empty status codes are toggled for existing locations as inventory is moved or adjusted in and out of locations.

2. Inventory in an Out-of-Service location is not available for order allocation.
3. You can change the status code of an existing location from In-Service to Empty. If there is inventory in the location, you will receive a warning message, but can still make the change.
4. If the installation has putaway rules that are looking for an empty attribute then the location status needs to be Empty, otherwise putaway will not look at empty locations for that line of the rule. Putaway finds a profile to use and then proceeds down the list until it finds room - i.e. it uses a first-fit method.
5. The status is never automatically set to Full; if you want the location to have a Full status, you must update it. (The triggers that handle Empty and In-Service do not handle Full status since the location contents would have to be recalculated each time something was moved into or out of it based upon the UOM on the plate.)
6. The only processing that tests for the Full condition is putaway. If the putaway rules indicate "anything goes" for a location (i.e. customers can be mixed) then it will NOT look at locations with a status of Out-of Service or Full.
7. If you attempt to delete a location with existing Lip's, an error message will be displayed and the action will be prohibited.
8. Each facility must have a Cross Dock Location. See the above section titled “Default Cross Dock Location”.
9. Each facility should have a location named “SUSPENSE”. This does not need to be a physical designation. The location type should be “Special”. This is used as part of the Cycle Count Processing.

Aisle

The field is optional and used for informational purposes and as part of the Visual Warehouse function.

Aisle Level

The field is optional and used for informational purposes and as part of the Visual Warehouse function.

Aisle Side

This setting is optional and used for informational purposes and as part of the Visual Warehouse function.

Description

The field is optional. It is useful to help new employees understand specialized locations (Assembly Area) when the location ID does not intuitively do this. A consistent use of intuitive

location IDs is preferred to the extensive use of the description field, which is not generally available to floor operations.

Section

The location section assists with determining how tasks are assigned. Values are maintained in the Section table, which is accessed by Setup/Facility/Location / Section Maintenance from the SYNAPSE menu. The field is required.

Mixing Allowed

These fields allow mixing products of differing characteristics at a location. The 3 checkboxes are not mutually exclusive. If Mixing Customers is checked then the other 2 are ignored. Similarly if Customers is unchecked and Items is checked then Lots are ignored. Appropriate messages are displayed to the RF operator at Putaway when trying to mix inventory when mixing is not allowed. The RF user can still drop the plates in the location but they are warned first.

Customers

Check this box to allow more than one customer to be stored at this location.

Items

Check this box to allow more than one item number (SKU) to be stored at this location. Caution: this may cause extra work for the staff at pick-up time, since the picker can no longer simply pick the closest available product, and must check for the proper SKU.

Lots

Check this box to allow more than one lot number (of the same item) to be stored at this location. This does not apply to Pick Fronts. If mixed lots are in the same Pick Front, the picker will be prompted to enter the plate for the pick so that the item can be lot tracked.

Velocity

Use this field to designate a location for items of a specific velocity; for instance, a facility may be set up to designate locations near the shipping doors for high-velocity (Velocity A) items. The field is optional.

- A – Velocity A (high velocity)
- B – Velocity B (medium velocity)
- C – Velocity C (low velocity)

If the “Use Velocity” option on the Putaway Profile is YES, the velocity code of the received item (on the Item/Specs/UOM tab) is considered in choosing a location for system directed putaway.

Note: There is no validation to prevent an item to be stored in a location with a velocity mismatch.

Weight Limit

Use this field to specify the weight limit of a location. Zero has the same effect as a blank value. The field is optional but is needed if a putaway rule uses “W” (weight) or “B” (Both weight and cube) as the Fit Method.

Count Interval: Days

This field is informational and be used for reporting purposes.

Last Counted

This field contains the last date that the location was counted (cycle count). Double Click on this field to navigate to the Cycle Count Activity Look-up screen. This is a non-enterable field.

Plate Count

This is the count of license plates at the location. It is the result of the count established at the last cycle count, modified by subsequent activity at the location. Note: If you attempt to delete a location with existing Lip's, an error message will be displayed and the action will be prohibited. Double click on this field to navigate to the Plat Look-up screen. This is a non-enterable field.


Pick Count

This is the count of picks from the location since the date Last Counted. It can easily be much greater than the Drop count, if, for instance, the operators regularly drop pallets and pick cases at the location.

Drop Count

This is the count of drops (putaways) to the location since the date Last Counted.

Location Maintenance/Zones



The entire Location/Zones screen is optional, but most locations are subject to picking and/or put away, and the zone and sequence for these operations are defined here. It is possible to enter the Zone field without the Sequence field, or vice versa, but you should treat the two fields as a unit, with both set to blank or both filled in.

Putaway Zone

This field defines the zone for the location. Values are maintained in the Zones table, which is accessed by Setup/Facility/Location/Zones from the SYNAPSE menu. The field is optional.

Putaway Sequence

Within the Putaway Zone, this field defines the order in which items will be dropped with a single putaway move. It is used if the RF operator selects the Location Sequencing option (LOC) during putaway.

1. In order for the putaway sequence to be effective, the sequence must be unique within the facility, not just the zone.
2. The field is optional. If no sequence number is available, the putaway sequence for the tasks will be random (i.e., unpredictable).

Picking Zone

Values are maintained in the Zones table, which is accessed by Setup/Facility/Location/Zones from the SYNAPSE menu. Updates are not allowed while a Physical Inventory is in progress for the facility. The field is optional.

Picking Sequence

Within the Picking Zone, this field defines the order in which items will be picked within a single picking task.

1. In order for the pick sequence to be effective, the sequence must be unique within the facility, not just the zone.
2. The field is optional. If no sequence number is available, the pick sequence for the tasks will be random (i.e., unpredictable).

Note: Picking sequence(s) are used during the picking process. Picking sequence does not create tasks nor have influence on task generation. For example, once a task is assigned to an individual, that individual will get all of the subtasks in picking sequence order.

Pick & Drop Location

Use this field to designate a location that can be accessed by at least two vehicle types, where items may be temporarily placed while moving, when one of the vehicles involved in the move cannot access the initial or final pickup or drop point. Values are maintained in the Locations table, which is accessed by Setup/Facility/Location/Location Maintenance from the SYNAPSE menu. The field is optional. The Pick & Drop Location may not be the same as the Location ID field. If none is defined here, SYNAPSE looks to the P&D defined for the zone.

Location Setup Wizard and Location Expert

- The Location Setup Wizard screen allows the creation, deletion or limited modifications of a group of locations that fit specific location ID criteria. Access the Location Setup Wizard by Setup/Wizards/Location Wizard.
- The Location Expert is used to modify individual locations after initial entry. Access the Location Expert via Setup/Facility/Location/Location Expert.

See the Synapse User Manual for more information on these features.


Section Setup

Setup/Facility/Location/Section Maintenance



Sections define areas of the facility that comprise sets of proximate locations, and control the assignment of work based on the next closest task section. Sections provide a mechanism for defining efficient transit pathways through the facility. The areas of the facility are designated with Section IDs and a section map is generated based on the geographical relationships between the sections. At the completion of a work task, SYNAPSE uses the section map to determine the next task for assignment. The preferred choice is another task in the operator's current section. If there is no pending work in the current section, SYNAPSE selects the closest nearby section for work assignment.

The best way to accomplish section definition is to build the Section table in three steps:

- Step 1 – Define /enter all the Section IDs for the facility from a floor map where you've laid out the IDs that you plan to use. Leave all the geographic connections blank.
- Step 2 – Methodically revisit each section record and complete the geographic entries, using the floor map to help you indicate which other sections are adjacent to the current section in each direction.
- Step 3 – Build the section map by clicking .

Section ID

The Section IDs must be unique within each facility. The ID is entered when you add a new section, and cannot be changed. (You may delete an incorrect section ID, and add the correct one.)

A Section ID may contain from 1 to 10 letters or numbers. Letters are automatically converted to upper case. Special characters are allowed but are not recommended. A simple approach is to divide the facility into a small number of areas and assign a 2-digit number to each.

You can use the look-up button  to view a list of the existing sections in the facility on the Section Lookup screen. See the “Section Lookup” section below. You may select an existing section record to update.

Directional Mapping

The remaining eight fields on the Section Maintenance screen enable you to identify the sections that adjoin this section in each direction. From your floor map of the facility (or a level of the facility), determine if there is another section in each direction. If so, enter that section ID where appropriate. It is never proper to enter the ID of the current section in one of the Directional Mapping fields. If there is a wall in a given direction, leave that direction blank – a person needs to go in some other direction, possibly through some other section, to get to a section on the other side of a wall. You only want sections to which direct transit is possible without needing to go through some other section first.

In the sample section pictured above, the facility has three wide aisles divided by a tunnel. We have designated Sections 01, 02, 03, 04, 05 and 06. The six section records were entered without filling in the directional mappings, and then the mapping for each section was entered. As you can see from the example, from Section 04 you can go directly north to Section 03, or you can go directly west to Section 02, or you can go northeast (“kitty corner”) to Section 05. Each of these three sections is presumed by SYNAPSE to be equally accessible and desirable from a standpoint of assigning work.

Northwest

If there is another section immediately to the northwest of this section, and transit is possible directly between this section and the section to the northwest, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

North

If there is another section immediately to the north of this section, and transit is possible directly between this section and the section to the north, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

Northeast

If there is another section immediately to the northeast of this section, and transit is possible directly between this section and the section to the northeast, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

West

If there is another section immediately to the west of this section, and transit is possible directly between this section and the section to the west, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

East

If there is another section immediately to the east of this section, and transit is possible directly between this section and the section to the east, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

Southwest

If there is another section immediately to the southwest of this section, and transit is possible directly between this section and the section to the southwest, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

South

If there is another section immediately to the south of this section, and transit is possible directly between this section and the section to the south, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.


Southeast

If there is another section immediately to the southeast of this section, and transit is possible directly between this section and the section to the southeast, enter the Section ID of that section here. Values are maintained in the Section table, which may be accessed from the Section Maintenance screen (this screen), from Setup/Facility/Location/Section Maintenance on the SYNAPSE menu. The field is optional.

Build Map

Use the Build Map button  to build the section map, after you have finished defining all the sections and entering all the mapping relationships. Later, if you make any changes to the sections or the mappings, use this button again to rebuild the map. Note: You must have supervisory access to the Section Maintenance screen in order to use the Build Map process.

When you click this button, a confirmation window appears.



- Click Yes or type Y or press Enter to confirm the request. When the build is complete, a message will appear on the screen.



- Click OK.


You can check in the Applications Message Log (Requests/Messages) to view your BUILD MAP messages.

The screenshot shows the 'Synapse 2 Application Messages' window. At the top, there are filters for User ID, Facility, Customer ID, Source (Author), Date Range (set to 10/31/2013), Type, Description, and a 'Record Limit' of 100. Below the filters is a 'Create Alert' button and an 'Alert Manager' button. A legend at the bottom indicates four message types: Error (red), Warning (yellow), Trace (green), and FYI (blue). The main area is a grid of log entries:

Created	User	Type	Source	Description	Facility	Customer	Last Updated
10/31/2013 5:02:12 PM	ANN	FYI	BUILDMAP	Successful end of section search map build.	ZET		10/31/2013 5:02:12 PM
10/31/2013 5:02:12 PM	ANN	FYI	BUILDMAP	Begin section search map build	ZET		10/31/2013 5:02:12 PM
10/31/2013 4:10:12 PM	ANN	FYI	BUILDMAP	Successful end of section search map build.	ZET		10/31/2013 4:10:12 PM
10/31/2013 4:10:12 PM	ANN	FYI	BUILDMAP	Begin section search map build	ZET		10/31/2013 4:10:12 PM

Section Lookup

The Section Lookup screen shows the section IDs and their current directional mappings (clockwise from North). It is accessed from the Lookup Button on the Section Maintenance screen.



The screenshot shows a Windows application window titled "Facility ZET Section Lookup". At the top left is a search bar labeled "Beginning with:" with a magnifying glass icon. Below the search bar is a table with 13 columns: Section ID, North, Northeast, East, Southeast, South, Southwest, West, Northwest, Last User, and Last Update. The table contains 6 rows of data, each representing a section mapping. Row 1 (Section ID 01) has a bolded "01" in the first column. Row 2 (Section ID 02) has a bolded "01" in the second column. Row 3 (Section ID 03) has a bolded "05" in the third column. Row 4 (Section ID 04) has a bolded "03" in the second column. Row 5 (Section ID 05) has a bolded "05" in the first column. Row 6 (Section ID 06) has a bolded "05" in the second column. The last column, "Last Update", shows dates ranging from 10/31/2013 4:07:47 PM to 10/31/2013 4:10:09 PM.

Section ID	North	Northeast	East	Southeast	South	Southwest	West	Northwest	Last User	Last Update
01			03	04	02				ANN	10/31/2013 4:07:47 PM
02	01	03	04						ANN	10/31/2013 4:08:11 PM
03			05	06	04	02	01		ANN	10/31/2013 4:08:51 PM
04	03	05	06				02	01	ANN	10/31/2013 4:09:18 PM
05					06	04	03		ANN	10/31/2013 4:09:41 PM
06	05						04	03	ANN	10/31/2013 4:10:09 PM

Zone Setup

Setup/Facility/Location/Zones



Zones define areas of the facility that comprise sets of proximate locations and control the grouping of picking and putaway tasks to make those operations more efficient. Furthermore, the additional fields on the Zones screen define a consistent set of picking rules for all the locations that are assigned to the zone.

Before you may begin adding zones to a new facility, you must have at least one Location defined with a PND (Pick and Drop) Location Type. If your zones don't require Pick & Drop transfer points, you can define a location record with a name like P&DNA for this purpose.

Zone (ID)

The Zones must be unique within each facility. The Zone ID is entered when you add a new zone, and cannot be changed. (You may delete an incorrect Zone ID, and add the correct one.) A Zone ID may contain letters or numbers. Letters are automatically converted to upper case. Special characters are allowed but are not recommended. Define zones based on the layout of the facility, and the need for specialized picking rules for related, proximate sets of locations.

You can use the look-up button  to access the Zone Look-up screen to lookup the table of existing zones in this facility or to select a zone to update.

Description

Enter a description of the use and general location of the zone within the facility (e.g., “Rack Storage South Central” or “Third Level Unit Picking, West”). This field is required.

Abbreviation

Enter a short name or description for the zone. This field is required.

Pick & Drop Location

Enter the location ID of a Pick & Drop location that may be used as a transfer point for the zone, when a vehicle cannot move into or out of the zone. This field is required. To select a location from a list, double click on the field to access the Location Lookup screen (Location Type is PND).

Default Pick Type

This allows the RF operator to select a pick type for his tasks. This is the pick type for the zone. If other pick types aren't selected during normal processing, the zone pick type is used. This field is required.

- BAT – Batch Pick
- LINE – Line Picking
- ORDR – Order Picking

Batch Pick Options

When the Default Pick Type is set to Batch Pick, this field can be edited.

Generate separate tasks

This option will allow separate pick tasks to be created. With separate pick tasks, multiple RF users can pick the product needed to be sorted for the order.

Sub-task limit

You can set a limit on the number of subtasks associated to each pick task.

Default Pick Direction

This field is informational only. This field is required.

- L – Label Pick
- P – Paper Pick
- R – RF Pick

Next Line Pick By

- Order - The next line pick will be set to pick by the next highest task id.
- Pick Sequence - The next line pick will be set to pick by pick sequence closest to the operator (either forwards or backwards; the system checks both ways).

Count After Pick?

- Yes - When an operator picks from a location, upon completing the pick, the operator will be redirected to the Cycle Count screen. The operator will perform a cycle count in the traditional manner with the exception that variances will result in a new cycle count task for the location rather than SUSPENSE balances. After the count is complete, the operator will be returned to pick task(s). If two operators are simultaneously picking from a location, only one user will be presented with the count task.
- No – Do not count a location after picking.

The default setting is based on the zone setting.

Pick Confirmation

Location

Check this box to require confirmation of the location for all picks in this zone.

Item

Check this box to require confirmation of the item for all picks in this zone.

Container

Check this box to require confirmation of the LIP'S for all picks in this zone.

Additional Information:

1. If License Plate substitution is permitted, the container check box must be on.
2. At least one of the Pick Confirmation options needs to be turned on for a Pick Zone.
3. Picking treats a lot tracked item being picked from a pick front, (regardless of the setting of Pick Confirmation Container for the picking zone of the pick front) identical to the way it would be handled if Pick Confirmation Container was selected. The picker needs to enter/confirm plates but can specify multiple LPs.
4. Updates are not allowed while a Physical Inventory is in progress for the facility.

Conveyor Picking Group

This section only has meaning if there is a conveyor used for picking in this zone.

Conveyor Picking Staging Area


Enter the staging location that is used for conveyor picks from this zone. This field is optional. You can select a staging location by double clicking on the field to access the Location Lookup screen (with Location Type STG). An operator doing conveyor picks will not need to enter a staging area.

Conveyor Picking Direction

- One-way - The assignment of tasks only goes forward in one direction.
- Back-and-forth - The assignment of tasks will go in two directions.

Allocation Rules Setup

Setup/Facility/Allocation Rules



Allocation rules allow you to control the selection of inventory in the facility for shipment and/or for replenishment. You may specify a set of steps that determine which inventory will be considered and in what sequence to satisfy an order. Each set of ordered steps is given a name, and that name can be assigned as a default action for a customer, and/or for each item of a customer, for picking and/or for replenishment. See the Customer Setup screen (Setup/Customer/Customer Maintenance) and the Item Setup screen (Setup/Customer/Item Maintenance) for further details. Both screens have a Facility Settings tab, where you can establish an Allocation Rule (for picking) and/or a Replenishment Allocation Rule. You can thereby specify specialized inventory allocation for every customer or item in the facility, if need be.

Allocation rules are set by facility. You must be working in the facility to create an allocation rule for the facility. (Use the Change Facility Option if necessary.)

During wave planning, for every item of every order, SYNPASE looks to see if there is an Allocation Rule that is assigned to the item. If there is not, it looks for a default Allocation Rule for the customer. When there is an Allocation Rule for the item or the customer, SYNPASE tries to allocate the order line item using the detail rules of the Allocation Rule.

Each unit of measure (UOM) ordered for an outbound order must have a corresponding entry on an allocation rule attached to the item. The system will attempt to follow the allocation rule before allocating other inventory that does not fit the rule to the order. If there is no allocation rule for the UOM, the system will not generate pick tasks.

Rule

The Allocation Rule names are unique to each facility. The Rule name is entered when you add a new rule, and cannot be changed. (You may delete a rule with an incorrect Rule name, and add the correct one.)

A Rule name may contain from 1 to 10 letters or numbers. Letters are automatically converted to upper case. Special characters are allowed but are not recommended.

You can use the Lookup button  to access the Allocation Rules Lookup screen. You can view a list of rules or select one to update.


Description

Enter a description of the use or general operation of the rule within the facility. The field is required.

Abbreviation

Enter a short name or description for the rule. The field is required.

Additional Buttons:




- Use the Renumber button to renumber the priority (sequence) fields in increments of 10. This leaves room for entering new steps.



- Use the Rules button to access the Allocation Detail Rule Maintenance screen and maintain the individual detail lines (steps) of the allocation rule.

Allocation Rule Details Maintenance



Each individual step of the allocation rule is defined here. The set of steps comprises the allocation rule.

Priority

The priority number is a sequence number – the lowest numbered priority step will be executed first. It is useful to add new records with priority increments of 10, in order to leave room to insert new rules later. If you forget, or run out of numbers while inserting, you can renumber all the steps in this allocation rule with the Renumber button, on the Allocation Rules Maintenance screen. It renames in increments of 10.

Premise

The premise fields act together as selection criteria. SYNAPSE looks for inventory that meets all the specified values in the fields of this group. If matching inventory is found in sufficient quantity to meet the order quantity, it is selected for shipment. Otherwise, SYNAPSE moves on to the next detail rule. The only required field in the group is Unit of Measure. This means that each detail allocation rule only applies to one specific unit of measure.

Order restrictions for Inventory Status and Class override all Allocation rules.

Most SYNAPSE installations sequence allocation rules using the largest UOM first down to the smallest.

Inventory Status

The field is optional. Enter a valid inventory status in this field to limit the detail rule to select inventory that has one particular inventory status. For instance, if the Premise Inventory Status is set to EX – Expired, SYNPASE will attempt to allocate inventory for shipments from expired stock, assuming the other Premise criteria are met. Such a rule could be used to clear out expired merchandise.

Inventory Class

The field is optional. Values are maintained in the ‘InventoryClass’ validation table. Enter a valid inventory class in this field to limit this detail rule to select inventory that has one particular Inventory Class. If no class value is entered, all inventory classes are considered based on the order.

Unit of Measure

The field is required. Values are maintained in the ‘UnitsOfMeasure’ validation table. Enter a valid UOM in this field to limit this detail rule to select inventory that has one particular Unit of Measure. For instance, if the Unit of Measure is set to EA - Each, SYNPASE will only apply this rule if the Order Unit of Measure is EA. For any other Order Unit of Measure, this detail will be ignored and SYNPASE will move on to the next detail allocation rule.

Minimum

The field is optional. If there is a value in this field, the detail rule only applies to order line items where the item order quantity is equal to or greater than the Minimum value. Otherwise, this detail rule is ignored.

Maximum

The field is optional. If there is a value in this field, the detail rule only applies to order line items where the item order quantity is less than or equal to the Maximum value. Otherwise, this detail rule is ignored.

Whole Units Only/Whole LP Only

Whole Units Only and Whole LP Only settings are available for allocation rules where the “Use Forward Pick ?” option is set to No.

Whole Units Only

1. Using this setting on an allocation rule will limit picking to whole units of the UOM.
2. If picking other UOM’s is possible, there must be an additional allocation rule sequence for that UOM. For example, if the order for SKU-A is for 250 ea or 2 ½ cases (100 ea = 1 case):
 - There must be allocation rules for cases as whole units only and eaches from the pick front or
 - There must be allocation rules for cases as whole units only from build and eaches as whole units only from bulk.

3. This setting is used in conjunction with the Label UOM and Label Qty for Label UOM fields on the Setup/Item Specs/Specs tab to allow pickers to pick small package orders at a higher level (carton level) and not at a Base UOM (each) level.

Whole LP only

This option is designed to allocate only whole license plates and fail if one isn't successfully located. When checked, this would force the allocation logic to attempt to fill demand, at least on this line, with full LP's, regardless of UOM and fail if that can't be done. When combined with Pick to Clean = Yes, it functions the same but just look through the LP's starting with lowest quantity first.

Where To Pick

The Where To Pick fields can limit the search for product to a specific location or zone.

Use Forward Pick?

- Yes - Picking is limited to the forward pick location(s) (Pick Fronts) for each ordered item. The Picking Zone field is closed to input.
- No - Forward pick location(s) (Pick Fronts) are avoided for each ordered item. The Picking Zone field is available for input to give you the option to limit the picks to a specific picking zone.

Picking Zone:

You have the option to limit the picking of items that meet the Premise criteria for this rule to a single specific Picking Zone. The field is optional. The Picking Zone field is gray (unavailable) if Use Forward Pick? is set to Y – Yes. When Use Forward Pick? is set to N – No, the Picking Zone field is available.

Double-clicking on this field accesses the Zone Lookup screen, from which you can select a zone for this field.

Tie Breakers

The Tie Breakers fields act to further control the selection of inventory for shipment. If more inventory than ordered meets the rule so far, the Tie Breakers will determine which inventory is chosen.

FIFO/LIFO

- FIFO - Allocation will occur on a First In/First Out basis.
- LIFO - Allocation will occur on a Last In/First Out basis.

FIFO/LIFO Date

- Manufacture - The FIFO/LIFO rule will be applied to the inventory's Manufacture Date.

- Expiration - The FIFO/LIFO rule will be applied to the inventory's Expiration Date.
- Lot - The FIFO/LIFO rule will be applied to the inventory's lot number. In the event that this option is chosen for an allocation rule and the rule is applied to items that do not track lot numbers and thus sorting by lot number is not feasible, receipt date will be used. This option is useful for customers that require inventory to be rotated by the lowest lot number.
- Receipt - The FIFO/LIFO rule will be applied to the inventory's Receipt Date. (This is the lower of Creation Date and Anniversary Date).

Strict (Replenishment Only)

This checkbox will only affect allocation for replenishments. When checked, the system will enforce strict FIFO when allocating. It will fail if it cannot allocate product per the settings configured within the oldest product available. Primarily this will be coupled with the "Whole LP Only" checkbox in order to not allocate small pallets that could be used to fill a pick front but that are significantly newer than larger pallets that won't fit in the pick front.

Pick To Clean?

- Yes – The system will attempt to allocate partial pallets found within the constraints of the rule first to fill the order.
- No – The system will not attempt to allocate partials first.

Note: If strict FIFO is desired, this setting should be set to No.

By Lot (Y/N)


The same lot will be allocated until the lot is depleted when this box is checked.

Additional FIFO/LIFO Information:

1. Overriding FIFO/LIFO picks is controlled by the FIFO window days settings for the customer, product group and item.
2. If a license plate is created via location load (RF option 91) or location fill (RF option 89), the receipt date is considered the date/time stamp the plate was created.

Frequently Asked Questions about Allocation and Task Generation

- I have commitments but no tasks for one of my order lines. What can I check?
 1. Check to see if the wave was released. If so, the allocation rules process but the GenPicks process can't actually create a task. For example, inventory in a license plate located in an Out of Service location will be allocatable and will commit but will not create a task.
 - I released my wave but there are no tasks for one of my order lines. What can I check?
 1. Check the Messages. Enter the order ID into the Description field to search to see if there was an allocation problem for the item. If you get a message here, the GenPicks process could not find inventory to allocate.



2. Look at the order detail line. Make sure it is:
 - a. Not cancelled
 - b. Not part of a planned cross-dock (shipping tab)
 - c. Was actually committed when the wave was planned – no commitments, no tasks
 3. Look at the inventory that you expected to task. The GenPicks process will not task inventory if it is:
 - a. In an Out of Service Location
 - b. In a Staging Location
 - c. In a Door Location
 - d. In the Wrong facility – not the from facility for the order
 - e. In an RF User ID Location
 - f. Not the status/class selection that was ordered – look at the order line detail.

4. Are there other tasks assigned to the plate you expect to see task?
 - a. There is an informational field, Quantity Tasked, in the lower left corner of the upper half of the license plate Additional Info1 tab.
 - b. Use this info to help research the situation.

The screenshot shows the 'License Plate Information' window for item 000010212013007. The 'Main Info' tab is active, displaying various fields such as Cust PO (P0765), Receipt Method (PL Pallet), Manufactured (10/21/2013 10:14:42 AM), and Quantity Tasked (10/21/2013). The 'Activity' tab is also visible, showing a grid of activity records:

Activity Date/Time	Item	Cust ID	Facility	Location	Plate Status	Inv Status	Hold Reason	UOM	Quantity	Type	Serial Number
10/21/2013 10:24:05 AM	BERRIES	INA	ZET	SYNAPSE	Moving	Available		Case	50	Pallet	
10/21/2013 10:17:04 AM	BERRIES	INA	ZET	SYNAPSE	Unassigned	Available		Case	50	Pallet	

At the bottom of the window, it says 'LINUX2TEST Facility ZET (Last Update by SYNAPSE at 10/21/2013 10:24:05 AM)'.

5. Look at the customer/item setup.
 - a. Is there an allocation rule selected?
 - b. Is one of the Kit options selected? Is the kit set up properly?
 - c. Check to see that the Item tab points to the facility for valid allocation rule for the from facility for the order.
 6. Look at the Allocation rule
 - a. Does the allocation rule include the UOM for the item?
 - b. Check to see if the allocation rule only points to a pick front (forward pick) for the quantity desired but no pick front exists for the item.
 - c. The allocation rule does not include the status/class selection that was ordered – look at the order line detail.
 7. Make sure the order was in a wave that was released after any changes to allocation rules or location status were updated.
 8. See if the order uses the Minimum Days to Expiration processing. If so, see if the available inventory fits the criteria for this order line.
- How are the final plates chosen?
 1. If FIFO is chosen, plates are sorted in ascending order, otherwise they are sorted in descending order. If Pick To Clean is selected, the plates are then sorted by quantity in ascending order, otherwise they're sorted by quantity in descending order. Finally, the plates are sorted by location in ascending order and lipid in ascending order.

Putaway Profiles Setup

Setup/Facility/Putaway Profiles



Putaway Profiles allow operations to control where inventory is stored in the facility. You may specify a set of rules (zones and qualifying characteristics) that determine what areas of the facility are searched for open storage space, and in what sequence. Each set of putaway rules is given a name, and that name can be assigned as a default putaway action for a customer, and/or for each item of a customer. See the Customer Setup screen (Setup/Customer/Customer Maintenance) and the Item Setup screen (Setup/Customer/Item Maintenance) for further details. Both screens have a Facility Settings tab, where you can establish a Putaway Profile. You can thereby specify specialized putaway rules for every customer and/or item in the facility, if required.

If there is no logical putaway location, the task will be assigned to “NOSPACE” and the operator will determine the putaway location.

Profile

The Putaway Profile names are unique to each facility. The Profile name is entered when you add a new profile, and cannot be changed. (You may delete a profile with an incorrect Profile name, and add a new profile with the correct name.)

A Profile name may contain 1 or 2 letters or numbers. Letters are automatically converted to upper case. Special characters are allowed but are not recommended.

You can use the Lookup button to access the Putaway Profile Lookup screen to view the table of putaway profiles in this facility and select a profile to update.

Description

Enter a description of the use or general operation of the profile within the facility. The field is required.

Abbreviation

Enter a short name or description for the profile. The field is required.

Disposition

Profiles may be specified for putaway, for returns, and for cross dock operations. Indicate which inventory disposition you are considering. The field is required but not used at this time.

Additional Buttons:

- Use the Renumber button to renumber the sequence fields in increments of 10. This leaves room for entering new detail lines.



- Use the View Zones button to access the Putaway Profile Rule Maintenance screen and maintain the individual detail lines (rules) of the Putaway Profile.

Putaway Profile Rule Maintenance

Zone ZONE01 Profile FC Facility ZET

Sequence: <input type="text" value="10"/>	Fit Method: <input type="text" value="P"/> Pallet
Zone: <input type="text" value="ZONE01"/> ZONE 01	Use Velocity? <input type="radio"/> Yes <input checked="" type="radio"/> No
Unit of Measure <input type="text" value="PLT"/> Pallet	Location Attribute: <input type="text" value="P"/> MixLot
Minimum: <input type="text"/>	Allow Putaway To Picking Locations? <input type="radio"/> Yes <input checked="" type="radio"/> No
Maximum: <input type="text"/>	
Inventory Status Values: <input type="text"/>	
Inventory Class Values: <input type="text"/>	
Product Group Values: <input type="text"/>	
Primary Hazard Class Values: <input type="text"/>	
LINUX2TEST Facility ZET (Last Update by ANN at 11/1/2013 11:09:58 AM)	

Each individual rule of the putaway profile is defined here. The set of rules comprises the putaway profile.

Sequence

The sequence number controls the action of the putaway profile – the lowest numbered sequence will be executed first. It is useful to add new records with sequence increments of 10, in order to

leave room to insert new rules later. If you forget, or run out of numbers while inserting, you can renumber all the rules in this putaway profile with the Renumber button. This field is required.

Zone

This field is required. You can double click on this field to access the Zone Lookup screen to select a zone for this field.

If this putaway rule can use any Zone in the facility, choose the ANY ZONE! option. It is not necessary to add an actual zone named ANY ZONE! to the table.

Unit of Measure

This field is required. Values are maintained in the ‘UnitsOfMeasure’ validation table. The receiving operator enters the UOM. There should be a putaway profile rule for each UOM the receiving operator may enter.

Minimum

This field is optional. The Minimum field sets the lower limit for consideration by the rule. If the license plate quantity is less than the minimum, SYNPASE proceeds to the next rule.

Maximum

This field is optional. The Maximum field sets the upper limit for consideration by the rule. If the license plate quantity is greater than the maximum, SYNPASE proceeds to the next rule.

Fit Method

This field is required. The initial value is set to “U” – Unit of Store. The fit method determines how an item based on the rule will be tested to see if it fits in each possible location.

Value	Name	Description	Additional Information
B	Both Cube and Weight	This method requires that the weight and cube both be considered when finding a location for a plate. Note: There must be a weight limit set for a location.	
C	Cube	The cube of the license plate is added to the cube currently in the location, plus the cube of any plates going to that location. The result is compared with the location cube capacity.	

Value	Name	Description	Additional Information
H	1 st Pallet Height	Under this method, the capacity of a location is a maximum number of plates. This maximum is the Standard Pallets (from the Unit of Storage for the location) times the stack height of the location. The stack height of the location is set by the stack height of the item of the first plate that is placed in the location.	<p>Example: If a location has a unit of storage with standard pallets of 6 and the first item dropped into the location has a stack height of 2, then the capacity of the location is 12 plates, regardless of any other item or plate that also gets put into that location. Locations can be over-filled and under-filled.</p> <p>The stack height of a location does not get reset until it has become empty and a subsequent plate is then dropped in it.</p>
P	Pallet	This method functions the same as the “S”tandard Pallet method but takes UOM into consideration.	See below, but considers Unit of Measure.
R	Replenish	The inventory can be directed to a pick front for the item if the pick front meets the criteria for replenishment.	<p>This method still matches (the plate) on Unit of Measure, Minimum, Maximum, Inventory Status Values, Inventory Class Values, Product Group Values and Primary Hazard Class Values; but only considers locations that are pick fronts for the item within the Zone and that match any specified velocity. The capacity is governed by the Maximum UOM and Quantity setup for the Pick Front. Any Location Attribute is ignored.</p> <p>Any pending replenishment tasks that will cause the capacity of the pick front to be exceeded will automatically be deleted or regenerated for a recalculated amount when the putaway is actually performed.</p>

Value	Name	Description	Additional Information
S	Standard Pallet	This method selects locations based upon LP count when finding a system-directed putaway location for a plate.	<p>This method ignores Unit of Measure, Minimum and Maximum but uses all the remaining criteria such as inventory status for a match.</p> <p>The capacity of a location is determined by the Standard Pallets quantity value for the location's Unit of Storage.</p> <p>If the current pallet count of a location is equal to or greater than the standard pallet quantity in the unit of storage, the system will not consider the location for putaway.</p> <p>When determining the number of plates at a location, only top-level plates (MP and standalone PA) are considered.</p>
U	Unit of Store	The quantity of the license plate expressed in units of store is added to the quantity of inventory in the same unit that is already in the location, and the result is compared with the capacity of the location in that unit of store. If the UOM are mixed, tries to convert to a common UOM.	To use this method effectively, the UOM to UOS relationship(s) must be defined for items.
W	Weight	The weight of the license plate is added to the weight presently in the location, plus the weight of any plates going to that location. The result is compared with the location weight capacity. Note: There must be a weight limit set for a location.	

Use Velocity?

- Yes - The received item's velocity (A, B, C) as set on the Item/Item Specs/UOM tab is considered when choosing a location.
- No - The received item's velocity (A, B, C) as set on the Item/Item Specs/UOM tab is not considered when choosing a location.

Location Attribute

This field is optional. If no value is chosen, any mixing is allowed. Configure this field to limit this detail rule to locations that have one of the following characteristics:

- A – Any Customers – Any mixing is allowed. This is the default value if no value is selected.
- C – Mix Product – Different Product but same customer. The rule will only consider a location for putaway if all of the inventory that is already in the location is owned by the same customer as the license plate.
- E – Empty - The rule will only consider a location for putaway if the location is in E status and no LPs are destined (by task) to go there. (See Additional Putaway Notes later in this chapter.)
- L – Same Lot – Same product and lot. The rule will only consider a location for putaway if all inventory that is already in the location is the same item and lot number as the license plate.
- P – MixLot – Same product but different lot. The rule will only consider a location for putaway if all of the inventory that is already in the location is the same item as the receipt item. Mixed lot numbers are allowed.
- RA – Same Receipt - The rule considers the location for putaway if all of the inventory is from the same receipt. The product and lot can be mixed.
- RP – Same Receipt/Same Product - The rule considers the location for putaway if all of the inventory is from the same receipt and the product is the same. The lot can be mixed.

Allow Putaway To Picking Location?

This option is designed to support operations needing to fill large locations with incoming inventory until picking starts against the location. At that point, putaway activity is switched to another location.

- No - This option is interpreted as follows:
 1. If there are any picking tasks against the location, then skip the location as a potential putaway candidate.
 2. If the location is not empty and it has been ‘picked from’ since it has been ‘putaway to’ then the processing skips the location as a potential candidate.

Note: Two location date fields “LastPickedFrom” and “LastPutawayTo” are updated by the picking and putaway logic. These fields are not visible from the location screen.

Inventory Status Values

This field is optional. Configure this field to limit this detail rule to received inventory that has one or more particular Inventory Statuses. Double-click on the field to access the InventoryStatus Code Lookup screen. Select multiple Inventory Status codes by double-clicking on each desired code, then clicking on the Select button to select the list.



Inventory Class Values

This field is optional. Specify this field to limit this detail rule to received inventory that has one or more particular Inventory Classes. Double-click on the field to access the InventoryClass Code Lookup screen. Select multiple Inventory Class codes by double-clicking on each desired code, then clicking on the Select button to select the list.



Product Group Values

This field is optional. Specify this field to limit this detail rule to received inventory that has one or more particular Product Groups. Double-click on the field to access the Product Group Lookup screen. The screen shows all Product Groups for all customers at this facility. If two customers use the same Product Group designator, there will be two entries for that Product Group. Select multiple Product Group codes by double-clicking on each desired code, then clicking on the Select button to select the list.

Primary Hazard Class Values

This field is optional. Specify this field to limit this detail rule to received inventory that has one or more particular Primary Hazard Classes. Double-click on the field to access the HazardousClasses Code Lookup screen. Select multiple Hazardous Class codes by double-clicking on each desired code, then clicking on the Select Button to select the list.

Hazardous Classes Code Lookup

Beginning with:			<input type="button" value="Select"/>	<input type="button" value="Clear Selections"/>
Legend: <input checked="" type="checkbox"/> Include Records selected = 0				
Code	Description	Abbreviation		
2.1	Flammable Gas	Class 2		
2.2	Non-Flammable Compressed Gas	Class 2		
2.3	Poisonous Gas	Class 2		
3	Flammable and Combustible Liquid	Class 3		
4.1	Flammable Solid	Class 4		
4.2	Spontaneously Combustible	Class 4		
4.3	Dangerous When Wet	Class 4		
5.1	Oxidizer	Class 5		
5.2	Organic Peroxide	Class 5		
6.1	Poisonous	Class 6		
6.2	Infectious Substance (Etiologic)	Class 6		
8	Corrosive	Class 8		
9	Environmentally Hazardous	Class 9		
9.1	Miscellaneous Hazardous	Class 9		
ORMD	Consumer Commodity ORM-D	ORM-D		

Additional Information on Multi-Plate Putaway

The putaway rule logic acts differently if the operator is attempting to putaway an Multi-Plate (MP) (as a single entity) which actually has multiple items:

1. The profile for the first item found as a child LP of the MP is the profile that is used - there is no guaranteed order.
2. If the items on the child LPs have mixed velocity, velocity is ignored in the search.
3. All inventory statuses for all child LPs are combined into one list and used for searching. The same is true for inventory class, product group and hazard class.
4. If mixed customers are found on child LPs, then putaway considers the MP to also have mixed items, lots and UOM's.
5. If mixed items are found on child LPs, then putaway considers the MP to also have mixed lots and UOM's.
6. If there are mixed customers, items or UOM's, then putaway automatically excludes fit type U – Unit of Store from the search.
7. If there are mixed customers, then putaway automatically excludes location attribute 'C – Mix Product', 'P – Mix Lot' and 'L – Same Lot' from the search.

8. If there are mixed items, then putaway automatically excludes location attribute 'P – Mix Lot', and 'L – Same Lot' from the search.
9. If there are mixed lots, then putaway automatically excludes location attribute 'L – Same Lot' from the search.
10. If there are mixed UOM's, then putaway assumes a quantity of 1 and a UOM of 'PL'.

Additional Putaway Notes

1. If the installation has putaway rules that are looking for an Empty attribute, then the location status needs to be Empty, otherwise putaway will not look at an empty location for that line of the rule.
2. It is not recommended to have a location attribute of "E" before a "non-E" in the rules (not to be confused with the E on the location). If the rules are setup with the E first, then the putaway process would look for an empty location before trying to place 2 LPs together. The facility would end up with 1 LP in each location before it tried to put more than 1 LP in a location.
3. If the putaway rules indicate "anything goes" for a location (i.e. customers can be mixed) then it will NOT look at locations with a location status of Out-of Service or Full. The only processing that tests for the Full location status condition is putaway.
4. When an operator logs in to the RF terminal, he has the choice of 3 modes:
 - T - for task directed putaway. Putaway tasks will be generated by the system that can be assigned to other operators.
 - S - for system directed putaway. The operator will be directed to a putaway location by the system as part of the receiving process.
 - O - for operator directed putaway. The operator will select the putaway location as part of the receiving process.
5. If the system is unable to find an appropriate putaway location, the RF operator will be shown a location of NOSPACE and the operator will select the putaway location.
6. If the "Putaway Highest Whole UOM" is selected on the Facilities/Options tab for the customer, item or product group, when you perform receiving you specify a UOM received and normally this is the UOM that putaway uses when scanning the putaway profiles. If this flag is set, then putaway will convert the base UOM and base quantity to the highest whole UOM for the item and use that for scanning the putaway profiles rather than the entered UOM.

7. Checking the “Restrict Putaway” box on the Setup/Facility/Options screen disallows RF operators from overriding Directed Putaway. It applies to RF functions 32 - Movement and 97 – LP Putaway. When activated the system will only allow manual overrides to locations within the designated putaway zone(s) in the item’s Putaway Profile. If the RF operator tries to put away an item in a location not in the putaway profile a “Loc is restricted” message appears. This is specifically developed for facilities where the putaway location and zone is crucial to the inventory and environment such as HazMat inventory.

A restriction to this “Restrict Putaway” option is that all items in the facility must have a valid Putaway Profile with designated locations. If there is not a valid putaway profile the RF operator will not be able to putaway the item. The operator will get the “Loc is restricted” message. At this point, the Restrict Putaway box must be unchecked for the putaway to continue.

CARRIER CODE SETUP

These screens are used to view and maintain the carrier codes and associated service codes. The carrier codes are used for both inbound and outbound orders. Carrier codes are valid for all customers. This section also contains information on the Automatic Assignment of Pro Number by Carrier feature. Preferred Carrier information is available in the Synapse User Manual.

Carrier Maintenance/Name

Carrier Maintenance ABF - ABF FREIGHT SYSTEMS

Name	Staging Locations	Delivery Service	Pro Numbers	Notification
Carrier:	Status:			
ABF	A			
Name:	Phone:	Logo:		
ABF FREIGHT SYSTEMS	330-673-8545			
Contact:	Fax:			
PH-330-673-8545 / FX 330-673-3277				
Address:	E-Mail:			
City:	State/Province:	SCAC:		
		ABFS		
Postal Code:	Country:	<input type="checkbox"/> Small Package Carrier		
	USA	<input type="checkbox"/> MultiShip Processing		
Delivery Tracking URL:	<input checked="" type="checkbox"/> Enable One-time Ship To			
Free Time Days:	Daily Demurrage:	Live Unload Time:		
Default Trailer Type:	Default Trailer Style:			
45	<input type="button" value=""/>			
LINUX2TEST Facility ZET (Last Update by ANN at 11/1/2013 1:57:42 PM)				

Carrier

All carrier codes must be unique with a length of not more than four-characters. This is a required field.

Status

Values are maintained in the ‘CarrierStatus’ validation table.

- A – Active
- I – Inactive

Name

This field contains the name of the carrier. This field is required.

Contact

Contact information for the carrier. This field is optional.

Address

This is the street address for the carrier. This field is optional.

City

This is the city of the carrier. This field is optional.

State/Province

Values are maintained in the ‘StateOrProvince’ validation table. Leave this blank for countries outside the U.S. and Canada. This field is optional.

Postal Code

Proper formats are 99999 and 99999-9999. Values are not edited for proper format or for agreement to the State/Province field. This field is optional.

Country

Values are maintained in the ‘CountryCodes’ validation table. This field is optional.

Phone

This is the primary contact phone for the carrier. The field is informational only and optional. The field is not edited for format.

Fax

The field is informational only and optional. The field is not edited for format.

E-Mail

This is the primary e-mail address for the carrier. The field is informational only and optional. The field is not edited for format.

SCAC Code

The Standard Carrier Alpha Code (SCAC) is a unique two-to-four-letter code used to identify transportation companies. This field is required.

Small Package Carrier

Indicates this carrier does small package processing.

MultiShip Processing

To perform MultiShip processing, check the Small Package Carrier box and check the MultiShip Processing box to interface to a Small Package system such as MultiShip or ClipperShip.

Enable One-time Ship To

If a One-time Ship To is allowed for the carrier, check the box next to Enable One-time Ship To.

Note: An order cannot have a One-time Ship To or a One-time Bill Freight To if this box is not checked.

Delivery Tracking URL

For carriers that have the MultiShip Processing box checked, easy access to the tracking support URL is allowed. Enter the appropriate URL link and a left and right curly brace set ({}) where the tracking number should be inserted in the Delivery Tracking URL field.

When the proper URL is added for a carrier and the tracking number is recorded on a shipping plate, you will be able to right click on a shipping plate lookup (or directly from the shipping plate screen) and, with appropriate internet access available, link to the carrier's tracking data for the tracking ID associated with the shipping plate.

Example URL:

`Http://wwwapps.ups.com/WebTracking/processInputRequest?HTMLVersion=5.0&sort_by=stat
us&tracknums_displayed=5&TypeOfInquiryNumber=T&loc=en_US&InquiryNumber1={}&Ag
reeToTermsAndConditions=yes&track.x=37&track.y=9`

Note: Carrier links can be obtained by looking up a tracking ID at the carriers website, noting the full address, and substituting a curly brace set for the tracking ID in the address. These addresses are subject to changes by the carrier at any time.

Free Time Days

Used for container tracking processing. This field is optional.

Daily Demurrage

Used for container tracking processing. This field is optional.

Live Unload Time

Used for container tracking processing. This field is optional.


Default Trailer Style/Type

Used for Yard Management processing. These fields are optional.

Logo

Used for the CRT Packing Screen. Right click to upload a bit map of the desired logo. This field is optional.

Carrier Maintenance/Staging Locations




This screen links specified staging locations with a carrier and shipment type. A specific staging location would be set up in this screen if orders for the selected carrier are always processed in the same location.

The staging location must already exist in the facility.

- To add an additional Staging Location, click the insert record button **+**. To view and select a staging location for the facility, double click the Stage Location field.
- Double click in the Shipment Type box and select a shipment type for the carrier/staging location combination.
- Click **✓** to save the data.
- Continue adding staging location/shipment type combinations as needed.

Carrier Maintenance/Delivery Service



Delivery service codes, the associated upgrade code and MultiShip translation code are entered on this screen. All delivery service codes and special service codes are associated with a specific carrier. These will be the codes used for the Outbound Order Delivery Service. The MultiShip Code is the code the Small Package system returns to Synapse as the Carrier Used.

If a delivery service is upgradeable on the Order Lookup screen, the upgrade code must be entered here for the carrier.

Additionally, valid Special Services Codes for the carrier are entered and maintained in the lower part of this screen.

Entering Delivery Service Codes

- Click the insert record button **+** in the service code section of the screen. Note: When entering this data for a carrier, enter the highest upgradeable code first, and then work down to the lower codes to insure that the upgrade code can be entered.
- Enter a unique Service Code for the carrier, a Description and an Abbreviation.
- Enter an Upgrade Code, if applicable. This must be an existing service code for this carrier.
- Enter the MultiShip translation code for this Service Code. The MultiShip Code is the code the Small Package system returns to Synapse as the Carrier Used.

- Click  to save your entry. The information will appear in the grid portion of the screen.
 - Continue until all Delivery Service codes have been added for this carrier.

Entering Special Service Codes

Carrier Maintenance UPS - UPS (UNITED PARCEL SERVICE)

Name	Staging Locations	Delivery Service	Pro Numbers	Notification	Navigation										
					◀	◀	▶	▶	+	▲	▼	✓	✗	✖	⟳
Service Code:															
2DAM		◀		◀	▶	▶	+	-	▲	▼	✓	✗	✖	⟳	
Description:		Abbreviation:		Upgrade Code:		MultiShip Code:									
SECOND DAY AIR AM		2ND AM				1									
Service Code	Description	Abbreviation	Upgrade Code	MultiShip Code	Last User	Last Up									
2DAM	SECOND DAY AIR AM	2ND AM		1	CANKLI	9/23/2012									
2DAY	SECOND DAY AIR	SECOND DAY		1	CANKLI	9/23/2012									
3DAY	3 DAY SELECT	3DAY		1	CANKLI	1/5/2012									
GROU	GROUND	GROUND		1	CANKLI	9/22/2012									
[View] [Print]															
Special Service															
SPC		◀		◀	▶	▶	+	-	▲	▼	✓	✗	✖	⟳	
Description:		Abbreviation:		MultiShip Code:											
Special Service		SPC		1											
Special Service	Description	Abbreviation	MultiShip Code	Last User											
* SPC	Special Service	SPC													
[View] [Print]															


- Click the insert record button  in the special service code section of the screen.
 - Enter a unique Special Service Code for the carrier, a Description and an Abbreviation.
 - Enter the MultiShip translation code for this Service Code.
 - Click  to save your entry. The information will appear in the grid portion of the screen.
 - Continue until all Special Service codes have been added for this carrier.

Carrier Maintenance/Pro Numbers


The auto-pro number assignment logic will look up the facility's geographic zone and then assign the pro number from the values maintained for that zone.

Facility Setup

The auto-pro number assignment logic looks up the facility's geographic zones and then assigns the Pro number from the values maintained for that zone.



Customer Setup



Automatic Pro Number Assignment

The Automatic Pro Number Assignment fields on the Customer Maintenance/Shipping/Options-1 tab support Pro number processing.

Consolidate Orders By:

When assigning Pro Numbers to consolidated orders, the system uses this field to determine which Synapse orders are auto-assigned the same Pro Number.

Carriers


An entry in this grid causes the auto-assignment to occur for outbound orders associated with the customer and carrier. The grid will contain the following fields:

- Carrier – The carrier ID from the Carrier table.
- Event – The event that triggers the auto-assignment. The events are:

- Load Close
- Wave Release

Note: If after automatic assignment, the system determines that the available unused pro numbers for a carrier is less than the minimum specified for that carrier, a warning message will be displayed.

Carrier Setup



The Pro Numbers tab allows for the display/maintenance of carrier-assigned pro numbers. The tab contains the following:

- Zone Grid – An entry is required for each Zone for the carrier even if the carrier only uses one zone.
- Min Unused Prono Count - An entry here enables a report to be produced that will inform you when more pro numbers must be obtained from a carrier. Additionally, if the carrier falls below the minimum, the display row on the carrier lookup screen is highlighted in yellow.

- Unused Count - The system will display the current count of unused pro numbers currently on file for the carrier regardless of zone. This box will be highlighted in yellow if the current unused quantity is below the minimum quantity.

Pro Number Grid

The grid contains the following fields for the Zone selected in the top grid:

Pro Number

The carrier's "progressive rotating" sequence reference number.

Sequence

When Pro numbers are imported, this sequence number will be set so that the imported Pro numbers are assigned on a FIFO basis. When you manually enter Pro numbers, the system will automatically set this sequence number, although a manual override will be allowed.

Assignment Status

Values are maintained in the 'PronoStatus' validation table.

- Unused – This status will initially be assigned to the pro number record to indicate the number is available for automatic assignment.
- Assigned – The Pro number value is assigned to an outbound order (or orders).
- Cancelled – Any Unused record can be changed to this status if the Pro number value is not to be automatically assigned.

Date/Time Assigned

The date and time the automatic assignment took place.

Assigned Order Id/Ship Id

These values will initially be blank and will be updated when the Pro number value is automatically assigned to an order.

Canceling a Pro number

To cancel a Pro number, right click on the line in the lower grid and select Cancel from the window. A cancelled Pro number can also be un-cancelled by right clicking and choosing Undo Cancel.

Carrier Lookup Screen

The Carrier Lookup screen displays the unused Pro Number Count and the Min Prono Count value. If the carrier falls below the minimum, the row is highlighted in yellow.


Carrier Lookup								
Beginning with:		State/Province:						
Carrier ID:		SCAC:	<input type="checkbox"/> Small Package Carrier <input checked="" type="checkbox"/> Active Status Only					
Legend: <input checked="" type="checkbox"/> Pro Numbers are needed <input type="checkbox"/> Inactive								
Carrier ID	Name	Contact	Phone	Status	State	SCAC	Min Prono Count	Unused Prono Count
3WAY	3WAY TRANSPORT	Mary Smith		Active	TN	3WAY	50	24
42FR	42 FREIGHT			Active		42FR	0	0
4SEA	FOUR SEASONS			Active		4SEA	0	0
905C	905 LOGISTICS % C H ROBINSON %			Active		905C	0	0
905L	905 LOGISTICS			Active	SC	905L	0	0
99TR	99 TRANSPORT			Active		99TR	0	0
A&I	A&I			Active		A&I	0	0
AACT	AAA COOPER			Active		AACT	0	0
AAMM	A AND M			Active		AAMM	0	0
ABBB	ABILENE TRANSPORTATION			Active		ABBB	0	0
ABER	ABERDEEN EXPRESS	1.800.248.2441, ext 11 For Dispatch	1-800-248-2441, ext 11	Active	OH	ABER	0	0
ABF	ABF FREIGHT SYSTEMS	PH-330-673-8545 / FX 330-673-3277	330-673-8545	Active		ABFS	0	0
ABFR	A & B FREIGHT LINES	KAY	800-231-2235/815-874-4700	Active	IL	ABFL	0	0
ABFT	ABERDEEN FREIGHT			Active		ABFT	0	0
ABIL	ABILENE TRANSPORTATION			Active		ABIL	0	0
ADLM	ABILENE MOTOR EXPRESS			Inactive		ADLM	0	0

Pro Number Import

An import procedure is available that allows Pro Number values to be loaded into the Synapse database. Any duplicate pro number values will be rejected and a message logged to Synapse's messages screen. Values are maintained in the 'PronoStatus' validation table.

1. The procedure will load the information for display/maintenance on the Carrier Pro Number tab.
2. The procedure is called "IMPORT_PRONO".

Carrier Maintenance/Notification



E-mails can be sent to Carriers when an inbound or outbound receipt load is closed. Configurable options allow e-mail to be customized for the recipient. When these options are configured for a carrier, an email will be sent to the email address or addresses (comma separated lists will be supported in the To Address) specified when a load of the appropriate type (receipt or shipment) is closed. This configuration uses the Oracle emailing functionality used elsewhere in Synapse.

The Email Body will accept the following wildcards:

Code	Description
%CARRIER%	Carrier code from the load.
%CARRIERNAME%	Full name of the carrier from the load.
%TRAILER%	Trailer number for load

	closed.
%LOADBOL%	Bill of Lading number.
%SEAL%	Seal from the load.
%PRO%	Pro number from the load.
%CLOSEDDATE%	Date the load was closed in mm/dd/yyyy format.
%CLOSEDTIME%	Time the load was closed in 24hr:mm format.
%REFERENCE%	Reference from the order(s) associated with the load. If there are multiples, a comma separated list appears.
%PO%	PO from the order(s) associated with load.

If there is multiples of an option, the email will display a comma separated list.

The list of wildcards for this function is less comprehensive than for some other emails so note the list above.

Security for Carrier Maintenance

Due to the specific processing needs for MultiShip and Small Package carriers, extra security is in place so that if you have access to the carrier screen in edit mode you cannot modify:

1. Small Package Carrier
2. MultiShip Processing
3. Enable One Time Ship To
4. Staging Locations Tab
5. Delivery Service Tab

Supervisor security is required to edit this information. This feature is only in effect if the default value, CARRIER_SECURITY, is set to Y.

Security Setup

Overview

SYNAPSE security setup is used to determine which screens a user or group may access and what privileges a user or group has for each CRT and RF screen (form). User-level security can be further restricted to limit access by specific facilities and customer accounts. For example, the staff in the billing office may only need access and privileges to a limited list of screens while a user in a supervisory role might need the rights to perform most functions in SYNAPSE.

Security Changes do not take effect until the user logs off and logs on again.

Security is setup in two stages:

1. Adding Groups
2. Adding Individual Users

Group

A group is a security profile created for a set of users who perform the same or similar job functions and thus have similar access needs. SYNAPSE allows the System Administrator to define:

- What screens a user in that group may access and
- What functions (view, add, delete, change) they may perform on that screen.

The Super Group

By creating a group and naming it SUPER, members of the group have full access to all CRT and RF screens without specifically adding the screens to the Group Settings list. To override the super access, the screen must be added to the Group Settings list with a permission setting other than "SUPERVISOR" for the override.


Note that a user in the SUPER group may have permissions that exceed their level of responsibility. For example, a user in the SUPER group may have the permission to delete a critical validation table. The SUPER group should only be assigned to a System Administrator and selected support users.

Individual User

Each SYNAPSE on-line and/or RF user is added as an individual user. A group profile may be chosen for the individual user. If a group is chosen, the individual automatically gets the screens and privileges defined for the group. The security administrator may override the group profile for specific screens and/or privileges or add functions to the individual user not in the group profile. An individual user's security can be restricted to limit access by specific facilities and customer accounts. Customer and facility restriction is not available at the group level.


Adding a Group

- Select Setup from the menu bar and click the Security Maintenance option. The Security Settings screen appears.



- Click the insert record button **+**.
- Click the Group button under User Type. The Group Info tab appears.

Warning: Do not select the Group button prior to clicking the insert record button. The application will update the currently selected user – changing it to a group.



Group Info Tab

When adding a group all the input fields except User, Name, User Type and Status unavailable for entry. Also note that there is no Customers/Facilities tab at the group level as this information is set at the user level.

- Enter the following fields:

Group

The group ID must be unique.

Name

This is a free-form text description of the group.


Status

Values are maintained in the ‘UserStatus’ Validation Table.

– Active

– Inactive – A user in this group cannot login to the system.

- Click the save changes button




Group Settings

The group settings are entered in the grid at the bottom of the screen. This grid is used to select the forms and access rights for the group.

Adding Forms

- Click the insert record button **+**. A list of all the SYNPASE form IDs appears.




- Click on the form that you want to add to the group and click OK.

Note: Refer to the charts at the end of this chapter for descriptions of the forms available.

Settings

Use the drop down menu to select an access setting for the form you selected. Options include:

- DISPLAY – Group members are allowed to view the data on the form.
- EDIT – Group members are allowed to add, update and delete the data on the form.
- SUPERVISOR – Allows Supervisor privileges on the form, if applicable.
- ACCESSDENIED – Group members are denied access to the form.



Note: Once an option from the list has been added, it will no longer show on the select form ID list.

- When you are finished adding forms and selecting settings, click the Group Settings save changes button .

Info Tab

The screenshot shows a Windows application window titled "Security settings for SHIPCLERK-Shipping Clerk Group". The window has a blue header bar with the title and standard window controls (minimize, maximize, close). Below the header is a toolbar with icons for back, forward, search, and other functions. The main area is divided into two sections: "Group Info" and "Info". The "Info" tab is selected, indicated by an orange background. The "Group Info" tab has its own toolbar with similar icons. The "Info" section contains fields for Title (Shipping Clerk), Address (two text boxes), City, State/Province, Phone, Fax, E-Mail, Postal Code, and Country. Below these fields is a "Group Settings" toolbar. At the bottom of the window is a status bar displaying the text "LINUX2TEST Facility ZET (Last Update by ANN at 11/5/2013 11:01:30 AM)".


Form	Setting
OrderForm	EDIT
ReceiveForm	EDIT

This is an optional form. Detail information on the group (i.e., Title, Address, Phone and Email information) can be entered.

Updating a Group

- Select Setup from the menu bar and click the Security Maintenance option. The Security Settings screen appears.

Warning: Do not select the Group button prior to clicking the look-up button. The application will update the currently selected user – changing it to a group.



- Click the look-up button next to the User field. The User Lookup screen appears.

User Lookup

Beginning with:	Facility:	<input type="text" value="SHI"/>	<input type="button" value="🔍"/>		
User ID:	Group:	<input checked="" type="checkbox"/> Active Status Only			
Legend: <input checked="" type="checkbox"/> User Group <input type="checkbox"/> Inactive					
User/Group	Name	Type	Group ID	Facility	Status
► SHINETSU	Shin Etsu Silicones of America	User	WEBGRP	11	Active
SHIPCLERK	Shipping Clerk Group	Group			Active
STAWIL	Stacy Wilcox	User	RFUSER	13	Active
STEFUR	STEVE FURY	User	RFUSER	18	Active
STEMUE	Steve Mueller	User	RFUSER	13	Active
STESMI	Steve Smith	User	RFUSER	11	Active
STETHA	Steven Tharp	User	RFUSER	18	Active
SUERAD	Sue Radabaugh	User	SUPER	11	Active
SUP	Supervisor	User	SUPER	ZET	Active
SUPER	Supervisor User	Group			Active
SUSLIA	Susan Lias	User	ACCT REP	11	Active
SUSPAR	Susan Parker	User	ACCT REP	17	Active
SWINCHELL	Sally Winchell	User	SUPER	ZET	Active
SYNAPSE	Synapse	User	SUPER	ZET	Active
TAMINCO	TAMINCO	User	WEBGRP	11	Active

- Enter criteria in the fields at the top of the screen to search for the group you want to edit. Click the process button .
- Double click the group that you want to edit. The Security Settings Group Info tab appears.

Security settings for SHIPCLERK-Shipping Clerk Group

User:	<input type="text" value="SHIPCLERK"/>	Group:	<input type="text"/>	Password:	<input type="password"/>						
User Type:	<input type="radio"/> User <input checked="" type="radio"/> Group	Facility:	<input type="text"/>	Re-enter:	<input type="password"/>						
Name:	<input type="text" value="Shipping Clerk Group"/>				Status: <input type="text" value="A"/> <input checked="" type="checkbox"/> Active						
Group Settings: <input type="button" value="−"/> <input type="button" value="+"/> <input type="button" value="✓"/> <table border="1"> <thead> <tr> <th>Form</th> <th>Setting</th> </tr> </thead> <tbody> <tr> <td>► OrderForm</td> <td>EDIT</td> </tr> <tr> <td>ReceiveForm</td> <td>EDIT</td> </tr> </tbody> </table>						Form	Setting	► OrderForm	EDIT	ReceiveForm	EDIT
Form	Setting										
► OrderForm	EDIT										
ReceiveForm	EDIT										
LINUX2TEST Facility ZET (Last Update by ANN at 11/5/2013 11:50:13 AM)											

Group Info

- Click the edit button  to update the information (User, Name, Status) for the group.

Note: A group can't be deleted, but you can change the status to Inactive.

- Click the save changes button  to save your updates.

Group Settings


To edit the available form and form settings, you can:

- Click the insert record button  to add a form to the group.
- Select the line and use the Setting drop down box to change the access for the form.
- Select the line and click the delete record button  to delete a form from the group.
- Click the save changes button  to save your updates.

Adding an Individual User


After the groups are added, you can add the individual users.

- Select Setup from the menu bar and click the Security Maintenance option. The Security Settings screen appears.



- Click the insert record button **+**.
- Make sure the User button under User Type is selected. The User Info tab appears.

Warning: Do not select the User Type button prior to clicking the insert record button. The application will update the currently selected user – changing it to a user or a group.



User Info Tab

- Enter the following fields:

User

The user ID must be unique.

Group

Use the drop down box to select a group. The individual will be assigned the same security settings as the group profile. Details of the Group Profile can be overridden in the User Overrides section at the bottom of the screen.

Name

Enter the name of the user in this is a free-form text box.

Facility

Enter the default facility for the user in the facility field. You can use the drop down box to select a facility from a list.

When the user logs in, this will be the assigned facility. Although the system does not require the entry of a facility value, it is suggested that one be entered otherwise the user must select a facility whenever he logs in to the CRT system. If there are license restrictions by facility, this field must be entered in order to have a successful login.

Password

Enter a password for the user. The user enters this password to login into SYNAPSE on the RF equipment or computer terminal.

Re-enter

Enter the same password to verify the password.

Status

Values are maintained in the UserStatus Validation Table.

- Active
- Inactive – The user cannot login to the system.

Note: The user ID can't be saved until Customers and Facilities have been updated.


Info Tab

This is an optional form. Enter details for the individual user here such as title, address etc. The same information can be viewed and updated on the Lookup/Employee/Info tab.

S Security settings for -

User Info	Info	Customers/Facilities					
Title: Supervisor	Phone: 800-746-5757						
Address: 1247 W. Park St.	Fax:						
	E-Mail:						
City: Metropolis	State/Province: IA						
Postal Code: 53667	Country: USA						
User Overrides:							
<table border="1"><thead><tr><th>Form</th><th>Facility</th><th>Setting</th></tr></thead><tbody><tr><td>▶</td><td></td><td></td></tr></tbody></table>		Form	Facility	Setting	▶		
Form	Facility	Setting					
▶							
LINUX2TEST Facility ZET (Last Update by at)							

Customer/Facilities Tab



The Customers/Facilities tab is used to determine what customer and facilities the user will have access to.

Note: Click the save changes button to save the user ID after updating this screen.

Change Facility

This option determines if a user can access more than the default facility set up on the User Info tab.

- No – The user does not have authorization to change facilities from the default facility selected on the User Info tab.
- All – The user has the authorization to change to all the facilities.
- Selected – The user has authorization for selected facilities. If this option is selected, a Selectable Facilities grid appears:

Facility	Group	Last User
DMJ	MANAGEMENT	ANN

- To add a facility, click the insert record button .
- Select a facility from the drop down box.
- Select a security group for the facility from the Group drop down box.
- Click the save changes button .

Selectable Customers

This option determines the customers that a user can access within the facilities.

- All – The user has access to all customers.
- Selected – The user has authorization for selected customers. If this option is selected, a Selectable Customers grid appears:

Customer	Last User	Last Update
0206	ANN	11/5/2013 1:5
INA	ANN	11/5/2013 1:5


- To add a customer, click the insert record button .
- Click the save changes button .

User Overrides

The User Overrides grid is at the bottom of all of the tabs. This grid is used to enter any authorization overrides to the group setting for this user. For example, the user has Shipping Clerk group authority, but needs supervisory authorization to Item Maintenance.

Form

- Click on the insert record button on the User Overrides navigation bar to add a form to the override. A Select Form ID appears:



- Click the form ID to select it.

Facility


- Use the facility drop down box to select a facility code.

Settings

- Use the drop down box to select a setting option:
 - DISPLAY – User is allowed to view the data on the form.
 - EDIT – User is allowed to add, update and delete the data on the form.
 - SUPERVISOR – User is allowed Supervisor privileges on the form.
 - ACCESSDENIED – User is denied access to the form
- Click the save changes button .

Updating an Individual User

- Select Setup from the menu bar and click the Security Maintenance option. The Security Settings screen appears.



- Click the look-up button next to the User field. The User Lookup screen appears.

User Lookup

Beginning with:	Facility:	<input type="text" value="CK"/>	<input type="button" value="🔍"/>		
User ID:	Group:	<input checked="" type="checkbox"/> Active Status Only			
Legend: User Group <input type="checkbox"/> Inactive					
User/Group	Name	Type	Group ID	Facility	Status
CKENT	Clark Kent	User	MANAGEMENT	ZET	Active
CLISCO	CLIFF SCOTT	User	RFUSER	11	Active
CORWIL	Cornelius Wilkes	User	RFUSER	15	Active
DALSWO	Dale Swope	User	RFUSER	11	Active
DANBRE	Dan Brenner	User	MANAGEMENT	11	Active
DANHIN	Dan Hinton	User	MANAGEMENT	11	Active
DANJAR	Daniel Jarrell	User	INVENTORY	13	Active
DANJOH	Danielle Johnson	User	ACCT REP	11	Active
DANLAW	DANA LAWSON	User	RFUSER	18	Active
DARKAM	Darrell Kamph	User	SUPER	11	Active
DEBBUS	Debra Bush	User	ACCT REP	15	Active
DEBGOS	Debbie Goson	User	ACCT REP	11	Active
DEBPOO	Deborah Poore	User	ACCT REP	16	Active
DENHOO	Dennis Hoover	User	RFUSER	11	Active
DENJOH	Denise Johnson	User	ACCT REP	11	Active

- Enter criteria in the fields at the top of the screen to search for the user you want to edit. Click the process button .
- Double click the user that you want to edit. The Security Settings User Info tab appears.

Security settings for CKENT-Clark Kent

User:	<input type="text" value="CKENT"/>	Group:	<input type="text" value="MANAGEMENT"/>	Password:	<input type="password"/>						
User Type:	<input checked="" type="radio"/> User <input type="radio"/> Group	Facility:	<input type="text" value="ZET"/>	Re-enter:	<input type="password"/>						
Name:	<input type="text" value="Clark Kent"/>										
Status:	<input type="button" value="A"/> <input type="button" value="D"/> Active										
User Overrides:	<input type="button" value=""/>										
<table border="1"> <thead> <tr> <th>Form</th> <th>Facility</th> <th>Setting</th> </tr> </thead> <tbody> <tr> <td>ItemForm</td> <td>ZET</td> <td>SUPERVISOR</td> </tr> </tbody> </table>						Form	Facility	Setting	ItemForm	ZET	SUPERVISOR
Form	Facility	Setting									
ItemForm	ZET	SUPERVISOR									
LINUX2TEST Facility ZET (Last Update by ANN at 11/5/2013 2:29:47 PM)											

User Info

- Click the edit button  to update the information (Name, Group, Facility, Password (Re-enter), Status) for the user.

Note: A user can't be deleted, but you can change the status to Inactive.

- Click the save changes button  to save your updates.

Info

- Click the edit button  to update the information for the user.
- Click the save changes button  to save your updates.

Customers/Facilities

- Click the edit button  to update the information (Change Facility, Customers) for the user.
- If Selected is chosen, use the navigation bars to update the Selectable Facilities and/or the Selectable Customers.
- Click the save changes button  to save your updates.

User Overrides

To edit the available form and form settings, you can:

- Click the insert record button  to add a form to the override.
- Select the line and use the Setting drop down box to change the access for the form.
- Select the line and click the delete record button  to delete a form from the override.
- Click the save changes button  to save your updates.

Cloning Group Settings and User Overrides

Cloning is a method for copying an existing override or group setting to another user or group. The entire record cannot be cloned; only the group settings or the user overrides.

Cloning Group Settings

- Select the group that you want to copy settings to.
- Click on the cloning button . A user lookup screen appears:

User Lookup

Beginning with:	Facility:	<input type="button" value=""/>			
User ID:	Group:	<input checked="" type="checkbox"/> Active Status Only			
Legend: <input checked="" type="radio"/> User Group <input type="radio"/> Inactive					
User/Group	Name	Type	Group ID	Facility	Status
1GRACE	Graceland	User		DMJ	Active
3TRF1	2.5 test rf user1	User	SUPER	JFW	Active
3TRF2	2.3 test RF 2	User	SUPER	JDG	Active
3TRF3	2.3 test RF3	User	SUPER	ZET	Active
3TRF4	2.3 test RF3	User	SUPER	ZET	Active
3TRF5	2.3 test RF5	User	SUPER	JDG	Active
AARFER	Aaron Ferguson	User	RFUSER	15	Active
ACCT REP	Account Representative	Group			Active
ALCOA	Alcoa	User	WEBGRP	13	Active
ALEGAR	Alejandro Garcia	User	RFUSER	15	Active
ALEWEB	Alex Weber	User	RFUSER	11	Active
ANDREW	Andrew Weber	User	SUPER	ZET	Active
ANGELA	Angela Yuan	User	SUPER	ZET	Active
ANGPRO	Angela Provens	User	ACCT REP	ZET	Active
ANN	Ann Denny	User	SUPER	ZET	Active

- Double click to select the group that you want to clone from. A confirmation window appears:



- Click Yes to copy the settings.


Cloning User Overrides

- Select the user that you want to copy overrides to.
- Click on the cloning button . A user lookup screen appears:

User Lookup

Beginning with:	Facility:	<input type="button" value="🔍"/>																																																																																																
User ID:	Group:	<input checked="" type="checkbox"/> Active Status Only																																																																																																
Legend: User Group Inactive <table border="1"> <thead> <tr> <th>User/Group</th> <th>Name</th> <th>Type</th> <th>Group ID</th> <th>Facility</th> <th>Status</th> </tr> </thead> <tbody> <tr><td>1GRACE</td><td>Graceland</td><td>User</td><td></td><td>DMJ</td><td>Active</td></tr> <tr><td>3TRF1</td><td>2.5 test rf user1</td><td>User</td><td>SUPER</td><td>JFW</td><td>Active</td></tr> <tr><td>3TRF2</td><td>2.3 test RF 2</td><td>User</td><td>SUPER</td><td>JDG</td><td>Active</td></tr> <tr><td>3TRF3</td><td>2.3 test RF3</td><td>User</td><td>SUPER</td><td>ZET</td><td>Active</td></tr> <tr><td>3TRF4</td><td>2.3 test RF3</td><td>User</td><td>SUPER</td><td>ZET</td><td>Active</td></tr> <tr><td>3TRF5</td><td>2.3 test RF5</td><td>User</td><td>SUPER</td><td>JDG</td><td>Active</td></tr> <tr><td>AARFER</td><td>Aaron Ferguson</td><td>User</td><td>RFUSER</td><td>15</td><td>Active</td></tr> <tr><td>ACCT REP</td><td>Account Representative</td><td>Group</td><td></td><td></td><td>Active</td></tr> <tr><td>ALCOA</td><td>Alcoa</td><td>User</td><td>WEBGRP</td><td>13</td><td>Active</td></tr> <tr><td>ALEGAR</td><td>Alejandro Garcia</td><td>User</td><td>RFUSER</td><td>15</td><td>Active</td></tr> <tr><td>ALEWEB</td><td>Alex Weber</td><td>User</td><td>RFUSER</td><td>11</td><td>Active</td></tr> <tr><td>ANDREW</td><td>Andrew Weber</td><td>User</td><td>SUPER</td><td>ZET</td><td>Active</td></tr> <tr><td>ANGELA</td><td>Angela Yuan</td><td>User</td><td>SUPER</td><td>ZET</td><td>Active</td></tr> <tr><td>ANGPRO</td><td>Angela Provens</td><td>User</td><td>ACCT REP</td><td>ZET</td><td>Active</td></tr> <tr><td>ANN</td><td>Ann Denny</td><td>User</td><td>SUPER</td><td>ZET</td><td>Active</td></tr> </tbody> </table>			User/Group	Name	Type	Group ID	Facility	Status	1GRACE	Graceland	User		DMJ	Active	3TRF1	2.5 test rf user1	User	SUPER	JFW	Active	3TRF2	2.3 test RF 2	User	SUPER	JDG	Active	3TRF3	2.3 test RF3	User	SUPER	ZET	Active	3TRF4	2.3 test RF3	User	SUPER	ZET	Active	3TRF5	2.3 test RF5	User	SUPER	JDG	Active	AARFER	Aaron Ferguson	User	RFUSER	15	Active	ACCT REP	Account Representative	Group			Active	ALCOA	Alcoa	User	WEBGRP	13	Active	ALEGAR	Alejandro Garcia	User	RFUSER	15	Active	ALEWEB	Alex Weber	User	RFUSER	11	Active	ANDREW	Andrew Weber	User	SUPER	ZET	Active	ANGELA	Angela Yuan	User	SUPER	ZET	Active	ANGPRO	Angela Provens	User	ACCT REP	ZET	Active	ANN	Ann Denny	User	SUPER	ZET	Active
User/Group	Name	Type	Group ID	Facility	Status																																																																																													
1GRACE	Graceland	User		DMJ	Active																																																																																													
3TRF1	2.5 test rf user1	User	SUPER	JFW	Active																																																																																													
3TRF2	2.3 test RF 2	User	SUPER	JDG	Active																																																																																													
3TRF3	2.3 test RF3	User	SUPER	ZET	Active																																																																																													
3TRF4	2.3 test RF3	User	SUPER	ZET	Active																																																																																													
3TRF5	2.3 test RF5	User	SUPER	JDG	Active																																																																																													
AARFER	Aaron Ferguson	User	RFUSER	15	Active																																																																																													
ACCT REP	Account Representative	Group			Active																																																																																													
ALCOA	Alcoa	User	WEBGRP	13	Active																																																																																													
ALEGAR	Alejandro Garcia	User	RFUSER	15	Active																																																																																													
ALEWEB	Alex Weber	User	RFUSER	11	Active																																																																																													
ANDREW	Andrew Weber	User	SUPER	ZET	Active																																																																																													
ANGELA	Angela Yuan	User	SUPER	ZET	Active																																																																																													
ANGPRO	Angela Provens	User	ACCT REP	ZET	Active																																																																																													
ANN	Ann Denny	User	SUPER	ZET	Active																																																																																													

- Double click to select the user that you want to clone overrides from. A confirmation window appears:



- Click Yes to copy the settings.

Additional Requirements for RF Users


All RF users must have a Unix/Linux login and password that matches the user name and password set up in this security screen. The system administrator normally does this.

- For ease of use for the RF operator, use a **simple lower case** user ID and password not to exceed eight characters. Keep in mind that the RF operator needs to enter this data every time they log in.
- Do not use a user ID that is also being used as a location ID. When an RF operator is moving a license plate, the location of the license plate becomes the RF User ID. If this is also a valid location, there may be processing issues.

RF Task-Level Privileges Set on the Employee Information Screen

Additional security restrictions for RF Task-level privileges are set up on the Lookup/Employees Employee Activity screen. This is optional and can be set using the Assignable Tasks entry box for the employee.

1. If a task is included for an employee on this screen, the user (or user's group) must have security granted for the screen.
2. If a task is excluded for an employee, this exclusion will override the security setting.
3. If tasks are set on this screen, the RF operator will receive the message "XX not enabled" or "XX disabled" where "XX" is a task type (i.e., CC for Cycle count).



CRT Form ID Chart

FORM ID	DESCRIPTION
ABCCycleRequestForm	Requests/Update Requests/ABC Cycle Counts/Create Cycle Counts
ActivityForm	Setup/Activity Codes
AlertContactsForm	Alerts Contacts
AlertManagerForm	Lookup/Alert Manager
AllocRulesHdrForm	Setup/Facility/Allocation Rules
ASNLookupDlg	Lookup/Receipt Information/Expected
BusinessEventsForm	Setup/Business Events
CancelLoadFlags	Production/Cancel Load Flags
CancelOrdersForm	Requests/Update Requests/Cancel Orders
CarrierForm	<p>Setup/Carrier Due to the particular system processing for MultiShip carriers, Supervisor security is required to edit the flowing fields.</p> <p style="text-align: center;">Small Package Carrier MultiShip Processing Enable One Time Ship To Staging Locations Tab Delivery Service Tab</p> <p>This feature is only in effect if the default value, CARRIER_SECURITY, is set to Y.</p>
CartonTypesForm	Setup/Container Types
CASNumbersForm	Setup/Item/Hazardous/SARA
CertAnalysisDig	Edit/Certificates of Analysis
CheckOrderEntryForm	Edit/Check Orders
ChemicalCodesForm	Setup/Chemical Codes
CommitmentsLookDlg	Lookup/Commitments
ConsigneeForm	Setup/Consignee
ConsolidateOrderDlg	Requests/Update Requests/Consolidate Orders
CreateLoadFlagForm	Production/Create Load Flags
CreateMLPrintSetForm	Production/
CreatePrintSetForm	Production/Create Print Sets
CreateReceiptDlg	Billing/Create Receipt Charges
CreateSPLoadFlagForm	Production/Create SP Load Flags
CriticalHolds	<p>Inventory Adjustments</p> <p>Users without "E"dit capabilities this option will be denied the ability to place inventory on any of the Critical Hold inventory statuses or take inventory off of them. The Critical Holds inventory Status codes are defined in the Critical Holds Validation Table.</p>
CustActvFacilitiesForm	Setup/Customer/Activities for Facilities

FORM ID	DESCRIPTION
CustItemChemBOLForm	from Right-Click menu on Order-Item Form
CustomCodeForm	Setup/Custom Code
CustomerForm	Setup/Customer
CycleCountRequestForm	Requests/Update Requests/Cycle Count
CycleCountSchedulerDlg	Requests/Update Requests/Count Scheduler
DeKitForm	Edit/Dekitting
DepickOrderForm	Edit/DePick Order (Aggregate Inventory)
DoorStageLocDlg	Lookup/Door and Staging Locations
EmployeeForm	Lookup/Employees
EndMonthClose	Billing/Accounting Close
EquipmentProfileForm	Setup/Equipment/Profiles
EquipmentTasksForm	Setup/Equipment/Tasks
FacilityForm	Setup/Facility/Facility Maintenance
FacilityPrinterForm	Setup/Facility/Printers
FmtValidationRuleForm	Setup/Format Validation Rules
ForceShipOrder	<p>Edit/Order Use with Caution</p> <p>The force shipment is invoked from a button on the Order screen. It only appears if the user has <u>Edit</u> (<u>and only Edit</u>) permission for this security option. It is used to force orders with zero ship quantities to a shipped status. This was designed for an end customer that could not accept a "cancelled order" -- they had to be shipped 0. It is illuminated if:</p> <ul style="list-style-type: none"> it is an outbound order it is in Entered status it is not on a Load it is not part of a Wave <p>When the user presses the Force Ship Order button, a verification message asks if they are sure. If the answer is affirmative the order goes to shipped status.</p>
FTZ216Authorized	Allows FTZ Authorization -- See Synapse User Manual
GoalTimeForm	Setup/Facility/Labor Standards Maintenance
HandlingTypesForm	Setup/Handling Types
ImportExportReqForm	Requests/Import/Export Requests
InvoiceRevForm	Billing/Create Receipt Charges
InvoiceSumForm	Lookup Invoices and Edit Billing (Not for Create- Lookup and Edit)
InvoiceViewForm	Billing/Create Invoice, Renewal Invoice, Receipt Invoice, Credit Memo, Miscellaneous Invoice, Accessorial Invoice

FORM ID	DESCRIPTION
ItemForm	Setup/Customer/Item Maintenance
LabelMaintenanceForm	Setup/Label Profiles
LabelRequestsDlg	Requests/Label Requests
LaborLookDlg	Lookup/Labor Activity
LaborMaintenanceForm	Setup/Security Maintenance
LaborReportLookDlg	Lookup/Labor Activity
LaborStandardsForm	Setup/Facility/Labor Standards
LoadFlagLookDlg	Production Module
LoadFlagRegenForm	Production Module
LoadPlatesForm	Edit/Load Plates
LoadsForm	Load Form
LoadStopForm	Load / Stop / Form
LoadStopShipForm	Load / Stop / Shipment / Form
LocationExpertDlg	Setup/Facility/Location/Location Expert
LocationForm	Setup/Facility/Location/Location Maintenance
LocationWizDlg	Setup/Wizards/Location Wizard
LocksForm	Utilities/Locks
MainForm	if 'S'upervisor, then "Utilities" menu item is displayed, otherwise its hidden
MoveInventoryForm	Edit/Move Inventory/Aggregate Inventory Rewarehousing
MoveTaskRequests	Right Click Menu on Plate Lookup Detail for Generate Move Tasks
MsgForm	Requests/Messages
MultiShipTerminalForm	Setup/MultiShip Terminal
NMFClassCodesForm	Setup/NMFC Codes
OperationalSummaryForm	Lookup/Operational Summary
OrderDuplicating	Edit/Orders (order header Order Duplicate function)
OrderForm	Edit/Order Editor/Order Maintenance (order header) and Edit/Multi-Order Editor Must have 'S'upervisor security to edit PO or Reference ID after an outbound order has shipped. See information about the Default Value, MULTIPASSTHRU_SUPERVISOR, for the Multi-Order Editor pass thru fields.
OrderFormItem	Edit/Orders (order detail)
OrderPickEntryForm	Edit Pick Entry
OutOrderSummaryForm	Lookup/Outbound Order Summary
PackingForm	Edit/Packing
PackingListsForm	Setup/Packing Lists

FORM ID	DESCRIPTION
PalletHistoryForm	Lookup Pallet History (Part of the Pallet Tracking Processing)
PalletInvTotDlg	Lookup Inventory Total (Part of the Pallet Tracking Processing)
ParseRuleForm	Setup/Parsing Rules
PhysicalInventoryAIEntryForm	Edit/Aggregate Inventory/Enter Physical Inv
PhysicalInventoryEntryForm	Edit/Physical Inventory Entry
PhysicalInventoryQueryForm	Lookup/Physical Inventory
PhysicalInventoryRequestForm	Requests/Update Requests/Physical Inventory
PickByLiPTaskRequests	Right Click Menu on Plate Lookup Detail for Pick Generation
PimManagerForm	Edit/Appointment Scheduler Must have a security setting of "E"dit or higher to make appointments
PlateAdjustForm	Lookup/Adjustments to Inventory See explanation for "INVADJSUPMODE" in default values for additional info on Security.
PlateForm	Lookup/License Plate Information Lookup/Inventory Totals
ProdRecvFGForm	Production/Receive FG from Production
ProdRecvWIPForm	Production/Receive WIP from Production
ProductGroupForm	Setup/Customer/Product Group Maintenance
ProductionMoveRequests	Right Click Menu on Plate, Lookup Detail for Generate Move to Production if PRODUCTIONMODE (default value) = Y
PurgeSetupForm	Utilities/Purge Setup
PutawayProfileForm	Setup/Facility/Putaway Profiles
QAForce	User must have supervisor authority of this function to force the completion of the inspection
QAInspection	User must have supervisor authority of this function to force the completion of the inspection using the RF option 84 (QA Inspection Screen)
QAInspectItem	Allows User to start QA inspection from the RF option 11 -- Receiving
QARequestForm	Requests/Update Requests/QA Inspection
QCHoldChanges	Right Click Menu on Plate, Lookup Detail for Plate on QC Hold + Hold
QueryofReceiptRatesForm	Lookup/Lot Receipt Rates/Query Lot Receipt Rates
RateForm	Setup/Customer/Rate Maintenance
RcptLookupDlg	Lookup/Receipt Information Actual

FORM ID	DESCRIPTION
ReceiptCloning	Edit/Orders The security must be explicitly defined for user to be able to clone a receipt order. The minimum setting of security for this feature is Edit.
ReceiveForm	Edit/Receive Load
ReceiveOrderForm	Edit/Receive Order (Aggregate Inventory)
RenewalFutureDate	Billing/Renewal Storage Request - processing for an entry checks if the renewal date is in the future and if it is requires the 'RenewalFutureDate' security parameter to be set to 'S' (or the user have Supervisor access)
RenewalReqDlg	Billing/Renewal Storage Request
ReopenReceipt	If this is set to "EDIT", the user can use the ReOpen receipt functionality on the loads screen where applicable.
ReplenishReqForm	Requests/Update Requests/Replenishment -- The Replenish Request and Customer Item forms contain a "Trace this request" checkbox. If the box is checked prior to a replenishment request, the system will generate "trace" messages (which will appear on the Messages Form under type "Trace Message"). The checkbox will only appear on the screen if the user has 'Supervisor' security, since these checkboxes are intended to be used for support/debug purposes.
ReportRequests	Requests/Report Requests Edit-level security only allows the user to execute the reports that are shortcuts (displays like a little book) Supervisory-level security allows the user to execute all the reports on the menu
ReturnsForm	Edit>Returns
RunOrderGroupingProcedure	Allows user to use the Specialized Order Grouping process in Wave Planning
SectionForm	Setup/Facility/Location/Section Maintenance User must have Supervisor Authority to use the "Build Map" function
SetItemSizesForm	Production/Set Item Sizes
ShipDaysForm	Setup/Facility/Ship Days
ShipmentSplitting	Edit/Orders The security must be explicitly defined for user to be able to split an outbound shipment. The minimum setting of security for this feature is Edit.
ShipOrderForm	Edit/Ship Order (Aggregate Inventory)

FORM ID	DESCRIPTION
ShippingPlateForm	Lookup/Shipping Plates User must have "S" access for the Restage button to illuminate.
StandardUOMConversionsForm	Setup/Standard UOM Conversions
StockConditionChanges	The ability to do an Inventory Adjustment for a License Plate
StorageParmsForm	Utilities/Storage Parameters
SupplierForm	Setup/Supplier
SystemDefaultsForm	Setup/Default Values
TablesForm	Setup/Validation Tables (Note that each Validation Table has specific security)
TasksForm	Lookup/Tasks The security restrictions on the right click menu items are as follows: Change Priority – requires Edit or Supervisor security Preassign To – requires Edit or Supervisor security Delete – requires Supervisor security Print Pick List – always available Reverse Paper Pick – requires Edit or Supervisor Print Pick Labels - always available Reverse Pick Labels – requires Edit or Supervisor
TMSServiceRoutesForm	Setup/Transportation Service Routes
TMSServiceZipForm	Setup/Transportation Service Zip codes
TrailerForm	Yard/Trailer Maintenance
TransOrderLookForm	Lookup/Transportation Orders
UnitOfStorageForm	Setup/Facility/Location/Units of Storage
UserForm	Setup/Security Maintenance
VelocityCalcForm	Requests/Update Requests/ABC Cycle Counts/Determine ABC Velocities
WarehouseUsageFrom	Lookup/Warehouse Usage
WaveProfileHdrForm	Setup/Facility/Wave Profile
WaveReleaseForm	Requests/Update Requests/Wave Release. The Wave Release screen contains a "Trace this request" checkbox. If the box is checked prior to the wave release, the system will generate "trace" messages (which will appear on the Messages Form under type 'T'race Message). The checkbox will only appear on the screen if the user has 'S'upervisor security, since these checkboxes are intended to be used for support/debug purposes.

FORM ID	DESCRIPTION
WaveSelectForm	Requests/Update Requests/Wave Planning
WaveTMSReleaseForm	Requests/Update Requests/TMS Release
WorkOrderAdministrationForm	Lookup/Work Orders
ZoneForm	Setup/Facility/Location/Zones

RF Form ID Chart

FORM ID	RF Option	Description
AIConversion	RF Option 76	AI to RF Conversion. Security for this option should be granted only during active conversions. Once a conversion is complete, it is recommended that the security for this screen be denied
RF1StepRec	RF Option 11	1 Step Receiving
RFAddItem	RF Option 11 RF Option 89 RF Option 91	Requires "S"upervisor or "E"dit to add item definitions via the RF in the specified RF options.
RFAnyPick	RF Option 51	Default / Any
RFAnyWork	RF Option 31	Any Work
RFASNRec	RF Option 12	ASN Receipt
RFBatchPick	RF Option 56	Batch
RFBldInspectLP	RF Option 86	Bld Inspect LP
RFBldMast	RF Option 75	Build Master
RFBldPway	RF Option 13	Build Pallet
RFBldRtnMp	RF Option 25	Build Rtn MP
RFBulkReturn	RF Option 22	Bulk Return
RFBulkUnload	RF Option 16	Bulk Unload
RFCharges	RF Option 93	Misc. Charges
RFClsRtnMp	RF Option 26	Close Rtn MP
RFClsSrtPick	RF Option 59	Sort Cluster
RFClustPick	RF Option 55	Cluster
RFCombMast	RF Option 44	Combine Master
RFConsolidate	RF Option 82	Consolidate MP
RFConveyor	RF Option 53	Conveyor
RFCycleCount	RF Option 35	Cycle Count
RFDamaged	RF Option 96	Damaged Items
RFDekit	RF Option 64	Dekit
RFDelRtn	RF Option 24	Delete Returns
RFDelUnk	RF Option 17	Delete Unknown
RFDePick	RF Options 48/72	De-pick
RFDockLoad	RF Option 41	Dock Loading
RFDockUnload	RF Option 43	Dock Unloading
RFDtlReturn	RF Option 23	Detail Return
RFFillLoc	RF Option 89	Fill Location

FORM ID	RF Option	Description
RFInspectLP	RF Option 78	Setting of "S" will allow the RF user to inspect the LPs.
RFInvAdj	RF Option 81	Inv Adjustment See explanation for "INVADJSUPMODE" in default values for additional info on Security.
RFItemInq	RF Option 88	Item Inquiry
RFKitLocs	RF Option 62	Kitting Locs
RFKitWork	RF Option 63	Work at Loc
RFKitWorkOrder	RF Option 61	Work Order
RFLipinspect	RF Option 78	Inspect LP
RFLocInq	RF Option 98	Loc Inquiry/Request Cycle Count for location Operator must have Edit or Supervisor access to request a Cycle Count from this screen.
RFLocLoad	RF Option 91	Location Load
RFLpInq	RF Option 92	Plate Inquiry
RFLpMove	RF Option 94	Move LP
RFLpPway	RF Option 97	Putaway LP
RFMatIssue	RF Option 87	Material Issue
RFMenu		Not needed for setup
RFMoveWork	RF Option 33	Movement
RFMtTrlr	RF Option 14	Empty Trailer
RFOrdCheck	RF Option 46	Order Checking
RFPhyInv	RF Option 36	Phys Inventory
RFPickupLP	RF Option 73	PickUpLP
RFProdFGRec	RF Option A3	Receive From Production (Production Module)
RFProdWIPRec	RF Option A2	WIP Receipt
RFProfile	RF Option 95	Profile
RFPutWork	RF Option 32	Putaway
RFQAIInspection	RF Option 84	QA Inspection
RFReArTrlr	RF Option 19	Re-arrive Trailer
RFReLabel	RF Option 74/85	Reprint LP
RFRelPway	RF Option 15	Putaway Rls
RFReplPick	RF Option 57	Replenish
RFReStage	RF Option 42	Restage
RFResumePass	RF Option 47	Resume Pass
RFSectionPick	RF Option 37	Section Pick - function is to interleave line picks and replenishment picks based on pick sequence within a section. Putaway tasks are not included.
RFShipAudit	RF Option 49	Shipping Audit


FORM ID	RF Option	Description
RFShipToProd		Production Module
RFSimpleSort	RF Option 38	Simple Sort
RFSortPick	RF Option 58	Sortation
RFSpltMast	RF Option 45	Split Master
RFSysOrdPick	RF Option 54	Order
RFSysPick	RF Option 34/52	Def Any Pick/Line Item
RFTakeItem	RF Option A4	Take Item (Production Module)
RFTopOff	RF Option 83	Loc Topoff
RFVoidLbl	RF Option 71	Void Labels

Frequently Asked Questions

1. Can an online user change their password?

Yes. You may do the following to change your password:

- Right click in the gray area of the screen and the following window appears:



- Select Change Password. The following screen appears:



- Enter your current password. Carefully enter the new password. Re-type the new password in the Re-enter New Password field.
- Click OK to confirm; otherwise click Cancel.
- The new password is available the next time you login in to SYNAPSE.

2. Does a SYNAPSE password expire?


No.

3. Can you have the same ID for the CRT and RF login?

Yes, but some installations like to keep them separate.

4. What do the CRT menus look like for users with restricted security?

The available choices are visible and the unavailable are grayed out.



5. What do the RF menus look like if I have limited security?

The RF menu system displays options to which you have access.

- All RF operators have access to option 99.
- If you don't have access to any options on a submenu then the submenu will not be displayed on the main menu.
- All options are displayed "rolled up" with no intervening blank lines.
- If you do not have access to an option or if the option does not exist, a "Not available" error message is displayed.
- The options that you have access to are determined only during logon. Changing your access while you are logged in will not change the menu structure until you log off and log on again.

Miscellaneous Setup Topics

Damaged Item Codes

RF Option 96 – Damaged Items uses the inventory adjustment module to do the required processing.

When you use option 96, you select a reason code from the Damage Item codes. When the damaged item transaction is processed, the inventory adjustment transaction is used, but it always passes the “CD” adjustment reason code. The reason code the operator enters on the screen is placed into the condition field of the plate.

To support this, the “CD” code must be in the following validation tables:

- AdjustmentReasons
- DamagedItemCodes

Customer Specific Validation Tables

You can set up tables that are specific to a customer to all customized processing. For example, if you only want a specific list of inventory classes available for a customer, you can set up the Class_to_Company table.

Class_to_Company_CCCCCCCCCC


The table (where CCCCCCCCCC is a valid Synapse Customer Identifier) contains entries that define the inventory classes that are available for a customer.

If this validation table exists, when inventory adjustments are performed (either via the desktop, RF or an import interface), only the Inventory Class value(s) defined in this table are available for this customer. Any other Inventory Class value will cause the adjustment transaction to reject.

If this table is not defined for a customer, then all Inventory Class values (as defined on the “InventoryClass” validation table) are allowed when performing adjustments.

The table entry format is:

- Code - This value must be a valid inventory class.
- Abbreviation - This value identifies a Company ID that can be used for export.
- Description - This is the code/process description.




Class_to_Warehouse_CCCCCCCCCC

This table (where CCCCCCCCCC is a valid Synapse Customer Identifier) contains entries that associate an inventory class to a virtual Warehouse ID for export purposes.

The Class_to_Warehouse table indicates which EDI_Parameters_for_CCCCCCCCC_WWWW table (described below) to use for inventory quantity, status, and class adjustments.

The table entry format is:

- Code - This value must be a valid Inventory Class.
- Abbreviation - This value identifies the Warehouse ID that can be used for export.
- Description - This is the code/process description.




EDI_Parameters_for_CCCCCCCCCC

This table (where CCCCCCCCCC is a valid Synapse Customer Identifier) contains entries which are used to configure EDI 947 (inventory adjustment) reporting.

Three codes must be defined in this table:

1. 947INVADJFMT
 - a. The abbreviation value must contain the 947 Export Format Identifier to be used when creating the customer's 947 export file.
 - b. The description value is available for text entry.
2. DMGSTATUS.
 - a. The abbreviation determines the inventory status code used to indicate damaged stock (usually the value 'DM').
 - b. The description value is available for text entry.
3. UNSTATUS
 - a. The abbreviation determines the inventory status code used to indicate unrestricted stock (usually the value 'AV').
 - b. The description value is available for text entry.



EDI_Parameters_for_CCCCCCCCCC_WWWW

This table (where CCCCCCCCCC is a valid Synapse Customer Code and WWWW is a virtual warehouse ID (as defined in the Class_To_Warehouse_CCCCCCCCCC table)) defines inventory adjustment reporting and restrictions for a virtual Warehouse ID.

There are three types of code entries in this table:

1. Quantity changes. Code format QQ-SS:RR where:
 - QQ is a constant of:
 - QI – for quantity increases
 - QD – for quantity decreases
 - SS is a valid Inventory Status Code.
 - RR is the reason code to be used for the adjustment.
2. Inventory Status Changes Code Format SC-FF/TT:RR where:
 - SC is a constant of ‘SC’ for Status Change
 - FF is the “from” inventory status (a value of ‘?’ represents all status values)
 - TT is the “to” inventory status (a value of ‘?’ represents all status values)
 - RR is the reason code (a value of ‘?’ represents any reason code)

- Abbreviation Usage
 - If a from/to combination is not allowed, then place the word ‘**Reject**’ in the abbreviation.
 - If a from/to combination is allowed, then place a movement code for export purposes in the abbreviation.
3. Inventory Class Changes Code Format “CC-FF/TT:RR” This format performs the same as the Inventory Status Changes Code Format.

SAP Parameters

The SAP_Parameters_for_(custid) define the export requests for the various order types in Synapse. If the SAP_Parameters order type entries are defined for the various export request events they will override the regular export setup at the customer level.

For each export event there are two sets of order type and format definitions that can be triggered. These are normally specified as the regular and return order types.

The export event and the associated sets of order type/format definitions that will be accessed from the customers **SAP_Parameters_for_(custid)** table are listed:

Ship Order from Order Screen

REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

Close Master Receipt from Order Screen

REGORDTYPES	REGI44RNFMT
RETORDTYPES	RETI9GIFMT

Force Ship Order from Order Screen

REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

Close Inbound Load from Loads Screen

REGORDTYPES	REGI9GRFMT
RETORDTYPES	RETI44RNFMT

Close Outbound Load from Loads Screen

REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

Close Order from MultiShip

REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

Order Cancel (zoe.check_cancel_interface)*For outbound orders ('O','V')*

REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

For inbound orders ('R','Q','P','A','C','I')

REGORDTYPES	REGI44RNFMT
RETORDTYPES	RETI9GRFMT

Receive Order Screen

REGORDTYPES	REGI9GRFMT
RETORDTYPES	RETI44RNFMT

Returns Screen

REGORDTYPES	REGI9GRFMT
RETORDTYPES	RETI44RNFMT

OrderItem Cancel Line causes Order cancel


REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

ShipOrder Screen

REGORDTYPES	REGI44SNFMT
RETORDTYPES	RETI9GIFMT

Example Setup

Code	Description	Abbrev
REGORDTYPES	Regular Order Types	O,R,T,A
RETORDTYPES	Return Order Types	Q,V
REGI44RNFMT	Zeth 944 Receipt Note	(format)
RETI9GRFMT	Zeth Returns	(format)
REGI44SNFMT	Zeth 945 Ship Note	(format)
RETI9GIFMT	Zeth Returns Shipment	(format)
REGI9GRFMT	Zeth Receipt Note	(format)

**Other Parameters that can be Configured**

REGWHSE - Regular warehouse reporting value
 RETWHSE - Returns warehouse reporting value
 I9INVADJFMT - Inventory Adjustment Extract Format
 UNSTATUS - Unrestricted (salable) statuses
 DMGSTATUS - Damage statuses

Default Values Setup

Setup/Default Values

Default Values

Parameter: ALLOWFULLFULLPICKTOLP

Value: N

Parameter	Value	Last User	Last Update
ALLOWFULLFULLPICKTOLP	N	JOEL	10/14/2013 01:07 PM
ALLOWFULLPACKPICKTOLP	Y	JSTANCYK	6/12/2012 11:23 PM
ALPHANUMERICCLIPS	Y	ZETHCON	1/25/2012 01:34 PM
APPROVALLIMITASSESSORIAL	5000	ZETHCON	1/25/2012 01:35 PM
APPROVALLIMITMISCELLANEOUS	5000	CANKLI	8/6/2007 10:30 AM
APPROVALLIMITRECEIPT	5000	JDG	1/23/2012 01:59 PM
APPROVALLIMITRENEWAL	10000	CANKLI	8/6/2007 10:30 AM
AR_ACCOUNT	10-1210	IRAHAM	12/1/2006 10:53 AM
ATTACHDIRPATH	F:\Synapse2\qa 2.5\PDFBOL	ZETHCON	4/20/2012 04:51 PM
BOLREPORT	\Shipping\BOLbase(ZSHPBOL).rpt	SWINCHELL	3/30/2010 02:21 PM
CARRIER_SECURITY	Y	SUP	6/8/2013 07:24 PM
CARTONSJOM	CS	JDG	8/14/2012 10:16 AM
CC_ITEM_SUMMARY	N	SWINCHELL	12/17/2012 02:17 PM
CC_LOC_EMPTY_PRIORITY	T	JSTANCYK	10/14/2013 07:10 PM
CC_NONE_CAN_PRIORITY	3	SYSTEM	1/1/2000
CC_NO_PICK_TASK_HOLD	Y	SUP	6/8/2013 07:24 PM
CC_REQUEST_PRIORITY	9	JSTANCYK	10/14/2013 07:11 PM
CONFIRMREACKNOWLEDGEMENT	Y	SWINCHELL	3/18/2013 04:26 PM

LINUX2TEST Facility ZET (Last Update by JOEL at 10/14/2013 01:07 PM)

This table holds the system parameters that allow options by installation. The values are rarely changed after the initial setup. Edit access to this table should be limited to the system administrator.

Default Values Chart

Following is a list of the parameters that can be set on the Default Values screen:

Parameter	Sample Value	Explanation
ACCEPTZEROQTYORDER	Y	If this value is set to "Y", orders with zero quantity detail lines can be taken off hold and processed. This is needed for EDI customers.
ALPHANUMERICCLIPS	Y	If set to Y, this setting will allow for the entry of alphanumeric LPs – as of version 1.7.2, the RF environment variable (ALPS_ALPHALPOK) is no longer used.
ALLOWFULLPACKPICKTOLP	Y	Allows full picks to be added to a Pick To LP items that are configured as PickToPack. Used with CONFIRMBLANKFULLPICKTOLP
ALLOWFULLFULLPICKTOLP	Y	Allows full picks to be added to a Pick To LP items that are configured as PickToFull. Used with CONFIRMBLANKFULLPICKTOLP
APPROVALLIMITASSESSORIAL	500	See Billing Concepts Manual -- User Defined Data for Billing
APPROVALLIMITMISCELLANEOUS	600	See Billing Concepts Manual -- User Defined Data for Billing
APPROVALLIMITRECEIPT	700	See Billing Concepts Manual -- User Defined Data for Billing
APPROVALLIMITRENEWAL	800	See Billing Concepts Manual -- User Defined Data for Billing
AR_ACCOUNT	234-9090	See Billing Concepts Manual -- User Defined Data for Billing
ATTACHDIRPATH	F:\Synapse\prod\PDF	Defines the full path name for PDF documents that are attached to order headers.
AUTO_PLAN_ONHOLD_ORDERS	Y	If set to anything other than 'Y' (including not being set), on-hold orders will NOT be automatically planned.
BATCHTOETYPE	TOTE	If no value is specified in the "Tote Type/Group" entry on the Wave Release/Options tab, the system will use this default value to determine the tote type value. If no default has been assigned, the system uses "TOTE" as the value.

Parameter	Sample Value	Explanation
BOLREPORT	\BOLBase.rpt	Path and name of the Crystal report to be used as the Bill of Lading Report; This can be overridden at the customer level -- See Concepts Manual - Customer - Shipping - Options 3. This is concatenated to the value set for REPORTSDIRECTORY. The system assumes that all automatically produced BOL's use load id as the input parameter for the Crystal Report.
CARRIER_SECURITY	Y	See the explanation in the Security Chapter of this manual for CarrierForm
CARTONSUOM	CTN	Used to calculate the order_cartons field in the ordercheckview
CC_LOC_EMPTY_PRIORITY	Values can be: 1 - immediate 2 - high 3 - normal 4 - low 9 - on hold T - same as the priority of the current task If any other value is entered into the default values table, the value 9 is used	Used when the RF operator responds with an "N" to the question "Is loc empty?". It sets the priority of the cycle count task that is created by the system.
CC_ITEM_SUMMARY	N	Used to control the Cycle Count Summary feature. The value is set to "Y" for the feature to be enabled and "N" for it to be disabled.
CC_NONE_CAN_PRIORITY	Same as for CC_LOC_EMPTY_PRIORITY	Used when the RF operator enters a valid reason on the "Can't Pick" screen under "Or No One Can". It sets the priority of the cycle count task that is created by the system.
CC_REQUEST_PRIORITY	Same as for CC_LOC_EMPTY_PRIORITY	Used when the RF operator responds with a C (requests a cycle count) to the question "Alt Loc (YNC)?" after pressing F6. It sets the priority of the cycle count task that is created by the system. Also used for cycle count tasks requested by an operator using the option 98 Location Inquiry.

Parameter	Sample Value	Explanation
CC_NO_PICK_TASK_HOLD	Y	Allowable values are Y or N. If the value is set to "Y", the system will not place pick tasks on hold and create a regeneration if the plate being picked is counted with a different value. If the value is set to "N", the normal processing will occur.
CHEPCUSTID	6789	The default CHEP customer id for the installation. If no value is entered on the Setup/Facility/Options tab, this value is used for CHEP pallet tracking exports.
CONFIRMBLANKFULLPICKTOLP	Y	<p>All RF picking screens are affected. The following conditions will invoke this functionality</p> <ul style="list-style-type: none"> • The item must be configured as Pick-to-Pack or Pick-to-Full at the pick unit of measure • The pick must be for a Full shipping plate • For pick-to-pack the system default ALLOWFULLPACKPICKTOLP (see above) must be set to 'Y' and for pick-to-full the system default ALLOWFULLFULLPICKTOLP (see above) must be set to 'Y' • The user must not enter an optional "Pick To" LP <p>When these conditions are met, the RF screen displays the message "New PickTo LP or Old" on the last line and the cursor will be positioned in the "Pick To" LP field. At which point the operator can either enter a new "Pick To" LP or use the old LP by leaving the field blank.</p>
CONFIRM_1STEP_LP_UPDATE	Y	IF set to Y, the operator will be prompted to respond to the prompt, "Update plate?", if the operator is using a plate that has already been created earlier in the receipt in 1-Step Receiving.

Parameter	Sample Value	Explanation
CUSTOM_SCHEMA	PECAS	Used for the Production Module. Defines the optional Oracle userid set up for custom code. This is currently used for looking up custom views and packages to include in the Label profile screen.
DAILY_BILLING_RUNTIME	0130	Default for Daily_Billing_Runtime for the time of day that the Oracle scheduled daily billing job is to execute. The format is HHMM. If nothing is set the default is 12:10 AM. For example - 1:30 AM would be set as 0130. If this default is changed, the system administrator will need to run the scripts, stop_daily_billing and then start_daily_billing. It will not read the time from the defaults until the next time it runs.
DAMAGEREPORT	\Inbound Order Damage.rpt	Path and name of the Crystal report to be used for the Inbound Order Damage Report - this is concatenated to the value set for REPORTSDIRECTORY.
DIRECT_TRAILER_LOADING	Y	While using Direct Trailer Loading, if this default is set to "Y" then the system will also automatically suggest the door location rather than a staging location.
DISPLAYENVIRONMENT	Y	A value of "Y" displays the name of the environment for the on-line user to view on the lower edge of the screen in addition to the facility id and the last update information.
ENABLE_SHIPPINGPLATEHISTORY	Y	A value of "Y" allows Synapse to create rows in the shippingplatehistory
EXPIRATIONDAILYJOB	EX	The expiration processing of DAILYJOB is triggered off this default value. If the default value does not exist, the expiration portion of DAILYJOB will not be executed. If a value is entered for this default value, it is the Expired Inventory status for the installation.
EXTENDEDNONTASKACTIVITY	N	IF this value is set to "Y", the RF Non-Task Activity Screen will allow the operator to enter a quantity and UOM. This info is informational only.

Parameter	Sample Value	Explanation
FREIGHT_COD_CHARGES	4021	Activity Code Default for the Freight Billing process
FREIGHT_FUEL_SURCHARGE	4020	Activity Code Default for the Freight Billing process
FOREIGNTRADEZONECLASSES	FT	See SYNAPSE User Manual - FTZ (Foreign Trade Zone) Processing
FORCESHIPMULTISHIP	Y	The purpose of this value is to do allow management users to clean up orders after some Mass Manifesting issues. Y will cause the 'Ship Order' button to appear for any small package MultiShip order which is in a status between 4 and 8 and the ship qty not equal to 0. Clicking the 'Ship Order' button will do all the processing that currently happens at shipment along with deleting all tasks/subtasks for the order. It will not delete any active tasks. Shipping plates are not updated.
FORMATSDIRECTORY		No longer used and has been removed from the form
FUEL_SURCHARGE	SU1	System Default if not part of customer setup for Freight Billing
FULLPLATEREPLENISHMENT	Y	If this value is "Y", only full pallets will be used for replenishment moves.
IMPEXP_TABLE		If this value is "Y" the import export request will be inserted into the impexp_request table. Used by limited customers.
IMPEXP_TRADITIONAL		If IMPEXP_TRADITIONAL is "Y" the import request works in the same way as before the addition of the default value IMPEXP_TABLE.
INVADJLOT	Y	This value is for a specific installation of Synapse that turns on the suspense inventory transactions the adjustment of the lot from the Adjustment screen.
INVADJMASS	Y	Y in this value allows the Mass Adjustment grid to display on the Lookup/Plate Plate Info form for the installation.

Parameter	Sample Value	Explanation
INVADJSUPMODE	Y	If this value is defined with a value of "Y", then 'E'dit security on the Plate Adjustment form will not allow changes to Customer, Item and Quantity. In order to change Customer, Item and/or Quantity, a user needs to have 'S'upervisor security. If the "INVADJSUPMODE" is not defined (or does NOT have a value of 'Y'), then 'E'dit and 'S'upervisor security make no difference. For RF, the 'RFInvAdj' form needs to be set to 'E'dit.
invoice	1105	See Billing Concepts Manual -- User Defined Data for Billing
INVOICE_WINDOW	35	See Billing Concepts Manual -- User Defined Data for Billing. Allows changing of the default window for creating an invoice from 30 days to the integer value specified.
INVOICEBASEREPOR	\InvBase.rpt	See Billing Concepts Manual -- User Defined Data for Billing - This is concatenated to the value set for REPORTSDIRECTORY.
INVOICEMSTRREPORT	\InvMstSum.rpt	See Billing Concepts Manual -- User Defined Data for Billing - this is concatenated to the value set for REPORTSDIRECTORY.
INVOICESUMMREPORT	\InvMstSum.rpt	See Billing Concepts Manual -- User Defined Data for Billing - this is concatenated to the value set for REPORTSDIRECTORY.
LABELCLIENTDROPDIRECTORY	\\\ntterm\Loftware\$\WDDrop	Where label request files are to be dropped (so that Loftware will find them to be processed)
LABELCLIENTFILEFILTER	Loftware Label Format (*.lwl) *.lwl	The file filter to be used in the label format file open dialog box
LABLECLIENTINIPATH		The path of the ".ini" file used by the Loftware server
LABELCLIENTLABELPATH	\\\ntterm\Loftware\$\LABELS	The path of the label directory
LABELCLIENTLAYOUTPATH	\\\ntterm\Loftware\$\LAYOUTS	The path of the layout directory
LABELCLIENTPRINTERPATH	\\\ntterm\Loftware\$	The path of the label printer

Parameter	Sample Value	Explanation
LABELCLIENTUSEFILEDROP		Supports WDDROP processing. A value = "Y" will have the radio group default to use file drop
LABORQTYPERHOUR	200	The default quantity per hour for a labor category (if no quantity has been defined for a particular category)
LBL_REQ_SCF_DIRECTORY		OBSOLETE -- To provide for the printing of labels from within Synapse (i.e. using the CRT) the smart compiled file must have the same name (without the extension) as the label file (.lwl) and reside in a directory (on the UNIX server) whose directory is identified by this default
LOOKUPINDEXCLASS1		The Class (as defined on the Utilities/Storage Parameters form) to be used for new validation table indexes (the system uses the class1 value for tables with an odd number of characters in their name. Class2 is used for tables with an even number of characters in their name. This allows for the definition of 2 separate table spaces for the system's validation table indexes if desired (if not desired, just make the class1 and class2 values the same)).
LOOKUPINDEXCLASS2		See LOOKUPINDEXCLASS1
LOOKUPTABLECLASS1		The Class (as defined on the Utilities/Storage Parameters form) to be used for new validation tables (the system uses the class1 value for tables with an odd number of characters in their name. Class2 is used for tables with an even number of characters in their name. This allows for the definition of 2 separate table spaces for the system's validation tables if desired (if not desired, just make the class1 and class2 values the same)).
LOOKUPTABLECLASS2		See LOOKUPTABLECLASS1
LOTRECEIPTRENEWAL	Y	See Billing Concepts Manual -- User Defined Data for Billing
LTLPOUNDSHIGH	1500	This value defines the high-end weight in pounds for the processing described below.

Parameter	Sample Value	Explanation
LTLPOUNDSLOW	201	This value enables the generation of a warning which informs the user if the weight of the order does not fit into the 'S'mall package, 'L'ess than truckload or 'T'ruckload category. This value defines the low-end weight in pounds for less-than-truckload assignment. If this value or LTLPOUNDHIGH is 0 or not specified, this processing is turned off. See the SYNAPSE User Manual Chapter on Preferred Carrier.
MASTERBOLREPORT	\MBOLBase.rpt	Path and name of the Crystal report to be used as the Master Bill of Lading -- this value needs to be set in order to produce a MBOL - this is concatenated to the value set for REPORTSDIRECTORY. The system assumes that all automatically produced BOL's use load id as the input parameter for the Crystal Report.
MASTERPACKLISTREPORT	\Masterpack1900.rpt	Path and name of the Crystal report to be used as the Master Packing List Report; This can be overridden at the customer level -- See Concepts Manual - Customer - Shipping - Options 3 and Customer - Shipping - Packlist - - this is concatenated to the value set for REPORTSDIRECTORY.
MAXLEFTOVERWEIGHT	5	The minimum weight value. If exceeded, the system will prompt the user with a warning. Load Close if there is a variance on a catch weight item/lot at the time of shipping. If there is no entry in this Default Value, this feature will be dormant.
MAXRFQTYLENGTH	5	See Concepts Manual -- Customer - Maximum Digits in RF Quantity
MIN0QTYSUSPENSEWEIGHT	.5	If there is a difference in the weight of a plate, a suspense entry will be created if the difference is greater than this value (even if there is NO qty variance, as in the number of units). This setting can be changed to a high value if the installation is not concerned with weights

Parameter	Sample Value	Explanation
MULTIPASSTHRU_SUPERVISOR	01,02,41,42	Settings for the Multi-Order Editor. A user must have "S"upervisor security to update any Header Pass Thru Field Codes listed in this default value.
MULTIPLATEOPTIONS	0	<p>This allows for defaults for the Lookup/License plate info/Plate info screen.</p> <p>Radio button options are for "All Plates", "Multiplates Only", "Exclude Multiplates". The system default settings will control the default setting for the screen. Any of the three options may be set as the default.</p> <p>Values can be:</p> <ul style="list-style-type: none"> 0 = All Plates 1 = Multi-Plates Only 2 = Exclude Mutli-Plates <p>If an invalid entry is made, the form will default to All Plates.</p>
MULTISHIPBUTTON	Y	Setting this value to a 'Y' will enable the Order Form's "Ship Order" button for manual shipment of Uncommitted>Loading (no outstanding commitments and order status = 7) Orders associated with a MultiShip Carriers. Additionally, the pick quantity must equal the ship quantity. The use of this value allows for enabling/disabling this functionality. If no action is taken or the value is set to "N", the functionality is not implemented
ORDER_GROUPING_PROC_PREFIX		This value defines a prefix that will be used to identify PL/SQL procedures for the Specialized Order Grouping During Wave Process Functionality.
ORDERBILLTAB	Y	Must be Y to allow the Billing Tab to be visible on the Order Header screen.
ORDERCHECKREPORT	\ord_check3.rpt	Path and name of the Crystal report to be used for the Order Check Report - this is concatenated to the value set for REPORTSDIRECTORY.

Parameter	Sample Value	Explanation
ORDERPRIORITYCOLOR	Y	This is used on the Wave Planning Screen to identify orders by ORDER PRIORITY based on the specific needs of a Synapse installation. Ship Short = Purple Hold = Green Use of this option does not affect the Red Highlight for Priority = Hot
PACKINGPRINTERDISPLAY	N	Value controls the printer drop down on the packing screen. This automatically defaults to Y. If this is set to N, the printer drop downs are hidden.
PACKLISTREPORT	\packlist.rpt	Path and name of the Crystal report to be used as the Packing List Report; This can be overridden at the customer level -- See Concepts Manual - Customer - Shipping - Options 3 and Customer - Shipping - Packlist - - this is concatenated to the value set for REPORTSDIRECTORY.
PALLETTYPECHEP		Used for the "I44_SHIP_NOTE" EDI transaction. This value is NOT part of the SYNAPSE Pallet tracking functionality.
PALLETTYPEWHITEBOARD		Used for the "I44_SHIP_NOTE" EDI transaction. This value is NOT part of the SYNAPSE Pallet tracking functionality
PALLETSUOM	PLT	Used in stored Procs for replenishment and wave planning.
PAPERPICKLISTREPORT	\picklist.rpt	Path and name of the Crystal report to be used for the Paper Picking report that is printed when an order pick task is assigned to paper on the task screen - this is concatenated to the value set for REPORTSDIRECTORY. This is not the report used for Aggregate Inventory Picking – see PICKLISTREPORT
PDFBOLPATH		Directory path for PDF BOLs with the embedded driver's signature. Setting the path will enable the PDF check boxes on the Customer/Shipping/Options – 3 tab for the BOL and MBOL..

Parameter	Sample Value	Explanation
PHYSICALINVENTORYREPORT	\Phy_inv_ticket.rpt	Path and name of the Crystal report to be used for the Paper Picking reports - this is concatenated to the value set for REPORTSDIRECTORY. This is not the report used for Standard Paper Picking – see PAPERPICKLISTREPORT
PICKFROMCHILDPLATES	Y	If this is configured “Y”, a pick will be generated for the Master Plate. Regardless of how the system processes the child plated, the system will then switch to a detail screen and scan the child plates until the pick is satisfied. This meets the needs for a specific customer.
PICKLISTREPORT	\agginv.rpt	Path and name of the Crystal report to be used as the Aggregate Inventory Picking Report; This can be overridden at the customer level -- See Concepts Manual - Customer – Shipping – Picking List Report Format - this is concatenated to the value set for REPORTSDIRECTORY. This is not the report used for Standard Paper Picking – see PAPERPICKLISTREPORT
PICKTYPELABEL	N	PICKTYPELABEL allows values = Y or N. Setting it to Y, turns on the Pick Type Label functionality. Works in conjunction with the values in the PIKTYPELABEL validation table
POCONFIRMATIONREPORT	\actrcpt.rpt	Path and name of the Crystal report to be used as the Receiver Report; This can be overridden at the customer level -- See Concepts Manual - Customer - Receiving Confirmation - this is concatenated to the value set for REPORTSDIRECTORY.

Parameter	Sample Value	Explanation
PRODUCTIONMODE	N	The value, "Y", Allows the Production Menu Screens to be accessible. The Production Module is specialized processing requiring additional tables and setup and should not be activated unless the database is set up correctly. Production Module is not available in 2.5.
PURGEAUTOUNLOCK		See SYNAPSE User Manual - Purge Overview
PURGEDEFAULTDAYS		See SYNAPSE User Manual - Purge Overview
QAFAILCONDITION		For automatically created QA inspections...defaults to BD, if not defined
QAFAILDISPOSITION		For automatically created QA inspections...defaults to UN, if not defined
QAPASSCONDITION		For automatically created QA inspections...defaults to GD, if not defined
QAPASSDISPOSITION		For automatically created QA inspections...defaults to OK, if not defined
QAPUTAFTERINSPECT	Y	The default value for the check box on the Requests/Inspection Info tab, "Request putaway after inspection".
QAPUTBEFOREINSPECT	N	The default value for the check box on the Requests/Inspection Info tab, "Request putaway before inspection". (meaning the inspection will *not* be taking place at the door and a putaway rule should route the 'IN'-status product to an inspection area)
RECEIVERREPORT	\exprcpt.rpt	Path and name of the Crystal report to be used as the Receiver Report; This can be overridden at the customer level -- See Concepts Manual - Customer - Receiver Report Format
REDUCEORDERQTYBYCANCEL	Y	When set to 'Y', the orderdtl trigger will reduce the qtyorder by qtycancel when line-item cancels occur.
REPLDEMANDPRIORITY		This value is no longer used and has been removed from the table.

Parameter	Sample Value	Explanation
REGENZONECONFIG	Y	If this value is set to Y, regenerated picks will generate with the task type configured for the zone in the Default Pick Type field.
REPORTTITLE	ACME Distribution	This can be used to add a standard report title to Crystal Reports, such as the company name. The report uses the reporttitleview. It joins the report title with a constant 1 called "truelink". The main report view needs to append the same constant to link with reporttitleview.
REPORTSDIRECTORY	\ntterm\synapse\ohldev\reports	This is the full path name for the main reports directory for the Crystal reports
REQUIREPALLETTRACKQTY	Y	The system will not require a pallet tracking quantity entry > 0 unless the value is set to a "Y".
RFPICKMODULE	SYSPICK2	The Value SYSPICK2 Activates an alternate "look" order picking screen which displays both the base quantity and unitofmeasure directly beneath the "to-be-picked" quantity and unitofmeasure.
SHIPDAYS	5	This value is used to calculate the automatic difference between the ship date and arrival date on outbound orders.
SHOWLABORLCUBE	Y	Shows Labor Reporting in Cubes.
SKIPRESTAGEDCLOSELABELCHECK	Y	Must be set to Y for functionality to process. Provides the ability not to reprint compliance labels on carton restaging for split shipments.
SMTP_BRACKET_ADDR	Y	Supports Oracle E-mail process. Indicates whether email addresses should be enclosed in angular brackets. If 'Y' then all email addresses will be surrounded by angular brackets (i.e. < and >)
SMTP_DOMAIN	yourcompany.com	Supports Oracle E-mail process. Domain name.
SMTP_HOST	smtp.yourcompany.com	Supports Oracle E-mail process. SMTP server host name.
SMTP_MAILER_ID		Supports Oracle E-mail process. if not specified, then 'Oracle UTL_SMTP' is used.


Parameter	Sample Value	Explanation
SMTP_PASS		Supports Oracle E-mail process. Password if authentication is required, otherwise not used.
SMPT_PORT	587	Required. Supports Oracle E-mail process. Mail port if other than 25.
SMTP_SENDER		Supports Oracle E-mail process. Sender email address, if omitted then synapse@SMTP_DOMAIN is used.
SMTP_USER		Supports Oracle E-mail process. Username if authentication is required, otherwise not used
SPECIALLIPCHARS		Used for a specialized inventory upload where the data contained special characters n the inbound lip.
SPLITORDERS	Y	This must be set to "Y" to allow partially loaded orders to be split into another shipment so it can be loaded on a second load.
SPOILAGEREASON	WD	This value is used by the Component Kitting function as the inventory adjustment reason code for the spoiled inventory processing at the end of the component kit processing. This value must be in the AdjustmentReasons Validation Table.
SUMMARIZEACCESSORIALLIMIT	100	See Concepts Manual -- User Defined Data for Billing
SUPPRESSNONPRODCARTONCOUNTS	Y	<ul style="list-style-type: none"> • If production mode is not turned on, this default value has no effect. • If production mode is turned on: <ul style="list-style-type: none"> – If the default value is set to an "N" [or it does not exist], then the system will operate as it does today (Carton count entry applies to all LiPs) – If the default value is set to 'Y', then the system will only request carton counts for LiPs associated with production orders.
SUPPRESSANNIVERSARYDATE	Y	Will defaults to N, if not ser. More information is under the Customer Name tab.
TASKPRIORITY		Not used at this time and has been removed from the table

Parameter	Sample Value	Explanation
TASKPRIORITYCC		Not used at this time and has been removed from the table
TASKPRIORITYRC		Not used at this time and has been removed from the table
TRACEFREIGHTBILLING	N	Used for Freight Billing processing
TRACKERURL		Not used at this time and has been removed from the table
UPGRADEREPLONRELEASE	Y	When set to a 'Y', all replenishment tasks (Type RP) associated with all Customer ID/Item combinations within the released wave, will have their priority upgraded one step.
URSAVALIDATION	OFF	The purpose is to validate all imported orders against the URSA table if the processing is turned on. Set the 'URSAVALIDATION' flag to 'ON' (note – this value must be uppercase). To disable, set the value to 'OFF'.
USEMULTISHIP		For future release of Synapse. Not used at this time
VICSBOLNUMBERAUTOGEN	Y	The value of Y, allows the AutoGenVicsBOL# process to execute to generate a unique for each shipment in a load. This is a customer specific application based on Header Pass Thru fields.
VIEWALLREPORTS	Y	This value set to 'Y' will force all reports to show in the Crystal Reports viewer first before printing. (It was created to solve a print issue for an installation using a Novell network)
VICSDECLAREDVALUE	\$2.30	Used in conjunction with the VICS BOL Server for the liability limit value printed on the VICS BOL.
WEIGHT_ROUNDING	N	Applies to the rounding rule for lbs. to kilo conversion. A rounding option = "Y" will follow the standard mathematical rules based on 8 decimal places. A rounding option of "N" will truncate the resulting weight to 8 decimal places. IF there is no rounding rule selected here or at the customer-level, the rule of N(o) will be applied to all lbs/kilo conversions.

Parameter	Sample Value	Explanation
WEBMAXODRCANCEL		Not used at this time and has been removed from the table
WEBPDFPATH	F:\Synapse2\Q2.5\PDFBOL	This defines the directory that the web server has access to, whether it is a directory on the web server or a shared directory on the app server. If using a network share, everyone must have read access on the directory. This works in conjunction with the value in the PDFBOLPATH and contain the files on the order attachment tab.

Validation Tables

Setup/Validation Tables



This screen is used to view and maintain the ORACLE validation tables for the installation of SYNAPSE. Any maintenance of the table values or the actual tables should be done under the direct supervision of the System Administrator.

Code Mask

The Code Mask defined for each table allows edit flexibility for the Code value. It determines the characteristics of the value that can be entered, i.e., numeric, 2 characters in length, etc. The following characters are used to define the Code Mask:

Description	Characters
Force Upper Case	>
Required Alpha	A
Optional Alpha	a
Separator	;
Numeric	9
Required Characters	C
Optional Character	c
Leave Special Characters	1 at end of mask
Don't Include Special Characters	0 at end of mask

Here are some examples:

>Aaaa;0;_	Force Upper Case; Require at least 1 alpha character; Allow up to 4 uppercase alpha characters; Show allowable length as “_”.
>9;0;_	Force Upper Case; Require at least 1 numeric character; Show allowable length as “_”.
>Ccccccccccc;0;_	Force Upper Case; Require at least 1 alphanumeric character; Allow up to 10 alphanumeric characters; Show allowable length as “_”.

Validation Table Maintenance

These tables hold the values that allow options by installation. Some values are used by the SYNAPSE logic and cannot be updated. An example of this is Item Velocity Codes. The Allow Header Update and Allow Detail Update boxes are left unchecked. Other values are updated for the installation. An example of this is the Adjustment Reasons Table. Edit access to validation tables should be limited to the system administrator.

If the User Update field is Y (Yes), you can change the Description and or Abbreviation of a table value with the appropriate security. Any table with a customer code in its name should have a Y in the User Update field. The system administrator needs Supervisor privilege to delete customer specific tables.

Validation Table Chart

Following is a partial chart of the validation tables.

Validation Tables that are highlighted in gray are not available for value update.

Validation Table Name	Description
ActivityMinimumCategory	Valid values to set Minimum Categories when defining activities for billing rate setup.
AdjustmentReasons	Valid installation-wide inventory adjustment reason codes.
AR Days	Used for specific Peachtree interface.
AutoPromptValues	Defines the options for adding billing charges.
BackOrderPolicy	Defines valid back-order processing options for outbound orders at wave release and order close.
BackOutAccessorial	Used for Revenue Report Setup.
BackOutMisc	Used for Revenue Report Setup.
BackOutReceipt	Used for Revenue Report Setup
BackOutRenewal	Used for Revenue Report Setup
BillByLocationActivity	Used by Billing to relate a location type to a billing activity so different rates can be set for each location type. Used for LUCT billing method.
BillingMethod	Valid bill methods used in billing rate setup.

Validation Table Name	Description
BillStatus	Valid Status codes for billing records viewed on the Edit Billing Charges Screen.
BusinessEvents	Obsolete – This has been replaced by the Setup/Business Events screen for Billing Charge and Label Printing Triggers. See Appendix A of this manual for more information.
CampusIdentifiers	Informational campus codes used for facility setup. Links facilities using multi facility picking option
CantPickReasons	Reason Codes used by operator during order picking when a "Can't Pick" situation is encountered. Also used for Lip Substitution Reasons.
CarrierStatus	Carrier Code Status - System logic based on value of "A" - Active. Synapse Installation may add other values.
CatchWeightOutboundCapture	Used in Catch Weight processing.
CommitStatus	Defines valid inventory commit status values for commitment/wave processing.
Class_to_Company_ZZZ	Use to associate a list of valid Inventory Class values with a customer. See additional information under the Customer/Shipping/Options-1 topic in this manual and Validation Tables for Inventory Adjustment Processes topic under Miscellaneous Setup topics.
Class_to_Warehouse_ZZZ	Used for EDI translations. See additional information in Validation Tables for Inventory Adjustment Processes topic under Miscellaneous Setup topics.
ConsigneeStatus	Consignee Status - System logic based on value of "A" - Active. Synapse Installation may add other values
ContainerTypes	Valid container types for the Setup/Item/Hazardous/SARA form
Contents_Status	Used for Yard management Trailers
Counted_by_Types	Valid for Transynd Transportation Management interface processing
CountryCodes	Valid list of country codes or address entry such as consignee or facility.
CriticalHolds	Valid list of inventory status codes that require specific security settings for user to make status adjustment.
CrossDockProcessing	Valid crossdock processing options
CustomerStatus	Customer Status - System logic based on value of "ACTV" - Active. Synapse Installation may add other values
CycleCountAdjustmentTypes	Valid cycle count inventory adjustment reasons.
DamagedItemReasons	Valid Damage Item Reason Code available to RF operator adjusting inventory to damaged using RF option 96.

Validation Table Name	Description
Delivery_Point_Types	Obsolete/Previously Used to define delivery point for Load/Shipment/Stop for VICS BOL processing.
EDI_BATCH_REF	Used for 944 EDI transactions
EDI_ID_HDR	Obsolete
EDI_PARTNER	Used for 944 EDI transactions
EDI_SENDER	Used for 944 EDI transactions
EDI_Parameters_for_CCCCCC CCCC	Used for EDI processing. See additional information in Validation Tables for Inventory Adjustment Processes topic under Miscellaneous Setup topics.
EDI_Parameters_for_CCCCCC CCCC_WWWW	Used for EDI processing. See additional information in Validation Tables for Inventory Adjustment Processes topic under Miscellaneous Setup topics.
EmployeeActivities	Defines valid employee activity codes viewed on the Labor Report Lookup Screen.
EquipmentProfiles	Defines all valid equipment profiles for the installation.
EquipmentTypes	Defines all valid equipment types for the installation.
ExpirationActions	Valid expiration action codes for customer and item set up.
FacilityStatus	Facility Status - System logic based on value of "A" - Active. Synapse Installation may add other values
FIFO_DATE	Valid options for FIFO date processing on the Allocation Rules form.
FitMethods	Valid fit methods for putaway profile definitions.
FormatValidationActions	Used to define actions when entered data does not fit assigned format validation rule. See User Manual for additional information.
FormatValidationData Types	Part of the definition rules for format validation processing. See User Manual for additional information.
HazardousClasses	Valid Hazardous Class for Chemical Code definition and Item Setup Hazard Class for Storage.
HoldReasons	Valid hold reason codes used when RF operator changes inventory status to Hold.
ImpExp_Queue	
InventoryClass	Valid inventory class codes.
InventoryStatus	Valid inventory status codes.
InvoiceTypes	Valid invoice types supported by billing processing.
IRIS_Del_Service_Exception	Used for IRIS billing interface processing.
IrisClasses	Used for IRIS billing interface processing.
IrisTypes	Used for IRIS billing interface processing.
ItemInventoryStatus	Valid item inventory status codes.

Validation Table Name	Description
ItemLipStatus	Valid item Lip status codes.
ItemStatus	Item Status - System logic based on value of "ACTV" - Active. Synapse Installation may add other values
ItemVelocityCodes	Used to define item velocity for location putaway selection and ABC cycle counting processing.
LabelPrintActions	Used as part of the Production Module Processing
LTLFreightClass	Used for Item setup.
LabelProfiles	An entry should be made here when a label is added to the Label Profile Maintenance
LaborReportCountGroups	Used for Revenue Report set up.
LaborReportGroups	Used for revenue report set up.
LateShipReasons	Valid reason codes for the Late Shipment Processing on Load Close
Last_xxxxxxxxxx	Typically used for EDI or other interfaces to record information about the last activity processed by the interface
LastTMSAll	Used by TMS processing. See User Manual for specifics.
LastTMS CustAll	Used by TMS processing. See User Manual for specifics.
Late Ship Reasons	Used on the Load Close screen if required
LoadArrivalPutawayDirections	
LicensePlateStatus	Valid license plate status codes.
LicensePlateTypes	Valid license plate types.
LipPropertyValues	Valid data capture codes
LoadStatus	Valid load status codes.
LoadTypes	Valid load type codes.
Loaded_by_Types	Valid for Transynd Transportation Management interface processing
LoadflagLabels	Used as part of the Production Module Processing
LocationAttributes	Valid location attributes used for putaway profile definition.
LocationStatus	Valid location status codes used informational purposes, putaway profile definition and inventory allocation processing.
LocationTypes	Valid location type codes used for informational purposes, putaway and inventory allocation processing, cross-docking, receiving, picking and shipping processing.
LotReceiptCapture	See Synapse Billing Manual for explanation.
LTLFreightClass	Obsolete...this processing now uses a different table.
LotRequiredOptions	Valid Lot Options for customer and item setup

Validation Table Name	Description
MessageAuthors	Provides list of values for lookup by Message Authors on Requests/ Messages/Synapse Messages Screen
MessageStatus	Provides list of values for lookup by Message Status on Requests/ Messages/Synapse Messages Screen
MessageTypes	Provides list of values for lookup by Message Types on Requests/ Messages/Synapse Messages Screen
MovementChangeReasons	Valid movement change reason codes used when the RF operator chooses an alternate location for a movement activity.
MultishipTermDate	Used to set up date format on some Multiship interfaces.
NationalMotorFreightClass	Used to define NMFC values for item setup.
NonTaskActivities	Provides list of activities such as break or meeting for RF operator when this RF option (Function Key 13) is chosen.
OrderCancellationReasons	Valid reason codes for order and order line item cancellation.
OrderItemStatus	Valid status codes for order line items.
OrderPriority	Valid order priority codes.
OrderQuantityTypes	Valid quantity types for an order line.
OrderStatus	Valid order status codes for all order types.
OrderTypes	Valid order type codes.
OrderValidationErrors	Valid order validation errors for orders imported via EDI.
PalletInvAdjReasons	Used by Pallet Tracking Processing when adjusting pallet inventory.
PalletTypes	Used by Pallet Tracking Processing
PalletWeights	Specific Pallet Weight Values for BOL report so that pallet weights can be added to shipped weight total when required.
ParseEntryField	Defines the valid item entry fields available for parse entry processing.
PhysicalInventoryStatus	Valid status codes for physical inventory activity records.
PickDirections	Valid values for The Default Pick Direction used in Zone setup.
PickRequestQueues	
PickToTypes	Valid values for Pick To Types used for Item setup.
PICKTYPELABEL	Works in conjunction with the default value PICKTYPELABEL
PickTypes	Valid pick types supported by the system.
PostalCodes	
PrinterStock	Valid Printer Stock types used for Setup/Facility/Printers.

Validation Table Name	Description
PrinterTypes	Valid Printer types used for Setup/Facility/Printers.
ProductGroups	Used for Product Group in Lookup screen filters. A value should be added here when a product group is added for a customer.
PronoStatus	Used to define the status of individual Pro Numbers as part of the Auto Pro Number Assignment processing.
PTInvoiceNames	Used for some versions of the Master Invoice Report and PeachTree Reporting
PutawayChangeReasons	Valid putaway change reason codes used when the RF operator chooses an alternate location for a putaway task.
PutawayConfirmations	Used to define putaway confirmation requirements for customer and item receiving set up.
PutawayQueues	
PutawayUnitDispositions	Valid values used to define disposition for putaway profiles.
QB_FAC_CLASS	Used for some customers that have Quick Books Interfaces
QCConditions	Used for QC processing. See SYNAPSE User Manual for specifics User Manual for specific information.
QCDispositions	Used for QC processing. See SYNAPSE User Manual for specifics User Manual for specific information.
QCRequestType	Used for QC processing. See SYNAPSE User Manual for specifics User Manual for specific information.
QCSampleType	Used for QC processing. See SYNAPSE User Manual for specifics User Manual for specific information.
QCStatus	Used for QC processing. See SYNAPSE User Manual for specifics User Manual for specific information.
RateCalculationTypes	Used by billing processing for rounding rules.
RateStatus	Used to determine status of Billing Rate. May not be updated to other codes.
ReceiptCondition	Receipt condition codes used by operator during returns processing.
RenewalStorageMethod	Obsolete Table; formerly used to support the "sqft" bill method.
ReplenishRequestQueues	
ReturnsDisposition	Used for customer setup to define customer default returns disposition and in item setup to define returns category for the item for returns processing.
RevenueReportGroups	Used for Revenue Categories when setting up Billing Activities.

Validation Table Name	Description
RFOperatingModes	Defines the RF operating modes chosen during RF login.
RoutingStatus	Valid values for the Routing Status field on the Order Header Shipping Tab for Outbound Orders
SARAPressures	Valid pressure conditions for the Setup/Item/Hazardous/SARA form
SARATemperatures	Valid temperature conditions for the Setup/Item/Hazardous/SARA form
ShipmentTerms	Used to define valid shipment terms on outbound orders
ShipmentTypes	Used to define valid shipment types on outbound orders
ShipperStatus	Supplier Status - System logic based on value of A - Active. Synapse Installation may add other values
ShippingPlateStatus	Used to define valid status codes for shipping plates.
ShippingPlateTypes	Used to define valid shipping plate types.
ShortShipReasons	Valid reason codes for order line detail for the Short Ship processing at Load Close
sip_parameters	Used to provide definitions for SIP processing (SPS Commerce interface).
StateOrProvince	Valid list of state and province codes for address entry such as consignee or facility.
StorageTypes	Used for informational purposes in location setup.
TaskPriorities	Used to define valid priority code for RF tasks.
TaskRequestQueues	
TaskTypes	Used to define valid task types to use in the lookup filter on the task screen.
TMS Status	Used by TMS processing. See SYNPASE User Manual for specifics
TMSArea	Used by TMS processing. See SYNPASE User Manual for specifics.
TMSCarriers	Used by TMS processing. See SYNPASE User Manual for specifics.
TMSFacilityGroup	Used by TMS processing. See SYNPASE User Manual for specifics.
TMSOrderStatus	Used by TMS processing. See SYNPASE User Manual for specifics.
TMSRoute	Used by TMS processing. See SYNPASE User Manual for specifics.
TMSStatusCode	Used by TMS processing. See SYNPASE User Manual for specifics.
Trailer_Activity_Types	Used for Yard Management
Trailer_Dispositions	Used for Yard Management

Validation Table Name	Description
Trailer_Status	Used for Yard Management
Trailer_Styles	Used for Yard Management
Trailer_Types	Used for Yard Management
UnitsOf Measure	Defines the valid units of measure used throughout the installation for inventory and billing purposes
UserStatus	User Status in Setup/Security Screen - System logic based on value of A - Active.
Vics_Bol_Types	Valid Types for the VICS BOL processing.
WaveStatus	Defines valid wave status values for wave processing.
WhenToAckOutbound	OBSOLETE – Formerly used to define timing options for Shipping Acknowledgement Transaction
WhenToConfirmOutbound	OBSOLETE – Formerly used to define timing options for Order Confirmation Transaction
WhenToVerifyPoReceipts	Used to define timing options for inbound PO Confirmation processing

Appendix A - Chart of Business Events

Business Events usually mark a change in status for an order, load or license plate or indicate that an activity has occurred. They are activities such as the close of an incoming load, the shipping of an order, or completing a cycle count. They are used to create billing amounts or to trigger the printing of labels. In billing, some business events generate sets of charges and others just create basic charges.

The codes for the supported Business Events are maintained via the Setup/Business Events screen. Since there is specific processing associated with each business event, the System Administrator maintains this table.

RF Prompt business events may be set as Prompted or Automatic.

Event Code	Description	Occurs When	RF Prompt	Label	Bill
ANDV	Anniversary Billing Renewal Storage by Day	Checked daily by background process to determine plates that need to have anniversary charges created.			X
ANVR	Anniversary Billing Renewal Storage	Checked daily by background process to determine plates that need to have anniversary charges created.			X
BILL	Billing Cycle After Renewal	At end of renewal billing. Used to determine if there are account minimums to apply.			X
CHEK	Order Checking	There are customer level auto and prompted charges for the CHEK business event. These launch after the user has responded positively to the prompt "Close Order?".	X	X	X
CKLP	Check License Plate				
CPCK	Customer Pickup	Applies to chargeable Will Calls (notification or coordination).			X
CYC	Cycle Count	As each plate is counted. Checks item rate group only.	X	X	
DMG	Damage Stock	After data is entered for the damaged plate. Checks item rate group only.	X	X	
EDAP	Edit Order after Picking Begins	Used when editing of an order in released through picked status. This allows billing to be added to these changes.			X

Event Code	Description	Occurs When	RF Prompt	Label	Bill
EMPT	Empty Trailer	After Empty Trailer (Option14) is complete. Checks customer rate group only.	X		
ENTR	AutoAdjustment Location Entry	Entering Auto Adjust.			X
EXIT	Auto Adjustment location Exit	Exiting Auto Adjust.			X
IAJ	Inventory Adjustment	After changes are made to a plate. Checks item rate group only.	X	X	
KIT	Kitting	Prior to putaway after a kit is complete. Checks item rate group only.	X	X	
LBPK	Label Picking	Used to Produce Labels for Label picking tasks.		X	
LDOP	Load Order Process	Triggers when order goes to loading status while loading plates.			X
LOAD	Loading	The LOAD event fires when the operator drops the plate in the trailer - i.e. the operator enters the Check ID for the Dock Door on the LP Loading screen.	X	X	
LTL	LTL (Non-Small Package) Ship Type	On outbound load close. Applies if order ship type is not small package (not = 'S'). Charges will be calculated for both order level and item level charges. This event is mutually exclusive with SMST (Small Package Ship Type).			X
MBOL	Master BOL	Charges triggered by the 'MBOL'" business event for each customer on the load if the load requires a master BOL.			X
MISC	Processing Miscellaneous Invoices	This is used for calculating minimums and surcharges when a miscellaneous recalc is performed from the 'Edit Billable charges' screen. It does not automatically generate any charges.			X
NOIB	No inbound pre-notification	Charges are added for each outbound order on the load with the order priority = ""N"" (NoNotify) when the order is shipped.			X

Event Code	Description	Occurs When	RF Prompt	Label	Bill
NONE	Not Triggered - Manually Entered	For documentation purposes only.			
ODAC	Order Creation (Add) via CRT	An order is added thru a CRT transaction and released from HOLD.		X	
ODAE	Order Creation (Add) via EDI	An order is added thru an EDI transaction.		X	
ODAW	Order Creation (Add) via WEB	An order is added thru a WEB transaction.		X	
ORCC	Order Cancel via CRT	An order is cancelled thru a CRT transaction.		X	
ORCE	Order Cancel via EDI	An order is cancelled thru an EDI transaction.		X	
ORCW	Order Cancel via WEB	An order is cancelled thru a WEB transaction.		X	
OSTG	Order Staged	Only recognized for the SCC14 Labeling. Does not generate LP labels or charges.			
P1PK	Prior to First Pick in Task	This event is triggered whenever an RF picker gets a new pick task - not replenishment or batch. Neither LP labels nor charges (auto or prompted) are associated with this event.		X	
PACK	Packing Complete	As each carton is packed.		X	
PFC	Pallet Full/Complete Pick	For each full pick and partial pick prior to staging. Checks customer and item rate group.	X	X	
PICK	Pick Stock	As each shipping plate is picked. Checks item rate group only.	X	X	
RCNX	Receipt Non-Cross Dock	On inbound load close for the receipt orders. Applies to quantities not sent to cross dock for planned cross dock orders. Determines automatic receipt charges. Should be used in tandem with RCXD.			X
RCXD	Receipt Cross Dock	On inbound load close for the receipt orders. Applies to quantities sent to cross dock for planned cross dock orders. Determines automatic receipt charges. Should be used in tandem with RCNX.			X

Event Code	Description	Occurs When	RF Prompt	Label	Bill
RECA	Receipt Arrival	Used for Pre-printing Receiving Labels.		X	
RECH	Receipt Handling	For each received LP prior to the start of putaway in one-step and ASN receiving. Checks item rate group only.	X	X	
RECO	Receipt Close	On inbound load close for the receipt orders. Determines automatic receipt charges.			X
RENW	Renewal Storage	On renewal request to determine renewal charges.			X
RETA	Returns Arrival				
RETH	Returns Handling	For each detailed return prior to the start of putaway. Checks item rate group only.	X	X	
RETO	Returns Order Close	On detailed returns complete. Used to calculate returns/receipt charges.			X
RPUT	Release for Putaway	After an LP is released for putaway using RF option 15. Checks item rate group only.	X	X	
RWAV	Release Wave	For Aggregate Inventory, allows user to request a shipping/picking label at wave release. Also used for automatic assignment of pro numbers by facility.		X	
SDSH	Same Day Ship	When Outbound Order with Priority = "S" (same day ship) ships.			X
SHIP	Ship Order Close	On outbound load close. Applies to all shipped items. Determines the shipping charges. Charges will be calculated for both order level and item level charges.			X
SMST	Small Package Ship Type	On outbound load close. Applies if order ship type is small package ('S'). Charges will be calculated for both order level and item level charges. This event is mutually exclusive with LTL - LTL Ship Type.			X
SPLO	Split Order Processing	Triggers for order split processing.		No Billing	

Event Code	Description	Occurs When	RF Prompt	Label	Bill
SPS	Small Package Shipment	On outbound load close. Applies if order shipping via small package carrier.			X
STPK	Stage Pick	This event fires for each staged plate at the time it is staged. Allows user to include the staging location on their shipping labels.		X	
STPR	Ship to Production	Used for Production Module Processing.			
TOUR	Complete Pick Tour	For each full pick and partial pick prior to any staging only when the last pick is picked. Checks customer rate and item group only.	X	X	X
VBCL	Void Bar Code Label	In cases where the customer is charged for each bar code label produced, this business event can be used to reduce the count of bar code labels if extra labels were produced and then not used.		X	
XDCL	Crossdock Close	Outbound Transload Order Ships.			X
XDRC	Crossdock Receipt	Inbound Transload Order Receipt Closed.			X

Obsolete Business Events – Not supported in current versions of SYNAPSE

Event Code	Description	Notes
CRPT	Customer Report Request	
DLFF	Destination Load Flag Format	Used for Production Module Processing.
FAXC	Fax Confirmation	
FPPP	Fetch PrePicked Pallets	Used for Production Module Processing.
MLFF	Mail List Load Flag Format	Used for Production Module Processing.
ORDC	Order Cancellation	Replaced by ODCC, ODCE, ODCW.
ORDR	Order Creation	Replaced by ODAC, ODAE, ODAW.
PRCL	Print Load Flag Carton Labels	Used for Production Module Processing.

REC1	Step 1 of 2-step Receiving	
RECP	Receive from Production	Used for Production Module Processing.
RECS	Receipt Storage	RECO - receipt close now provides this function.
SEA	Shipment by Sea	
SLFF	Small Package Load Flag Format	Used for Production Module Processing.

Appendix B - Chart of RF Employee Activity

This chart summarizes the source of the data displayed on the grid in the Lookup/Employees/Employee Activity screen.